# 1 Logging Data From Serial Ports Exercise

## Exercise 1.

Import the serial module and open the serial port with the appropriate parameters.

## Exercise 2.

Get a reading from the temperature probe.

#### Exercise 3.

Add a date and time reading to your output, using sensible choices for format, timezone, etc.

## Exercise 4.

Add a loop to your code to continuously log the reading and time. What would be a good exit condition? Hint: try dir(serial.Serial) to see what methods might be of use.

#### Exercise 5.

Rewrite your code to use readline().

## Exercise 6.

Alter your code to write the data out to a file.

## Solution 1.

```
#!/usr/bin/env python
import serial

ser = serial.Serial(
    port='/dev/ttyUSB0',
    baudrate=9600,
    bytesize=serial.EIGHTBITS,
    parity=serial.PARITY_NONE,
    stopbits=serial.STOPBITS_ONE
)
```

#### Solution 2.

```
print(ser.read(size=8))
   "8" here is specific to the Papouch thermometer device.
```

#### Solution 4.

Several ways, but the simplest is:

```
while ser.isOpen():
   datastring = ser.read(size=8)
   print datetime.utcnow().isoformat(), datastring
```

## Solution 5.

```
import io
...
sio = io.TextIOWrapper(io.BufferedRWPair(ser, ser, 1), encoding='ascii', newline='\r')
while ser.isOpen():
   datastring = sio.readline()
   print datetime.utcnow().isoformat(), datastring
```

## Solution 6.

```
#!/usr/bin/env python
'''This version of the readserial program demonstrates
using python to write an output file'''
from datetime import datetime
import serial
import io
outfile='/tmp/serial-temperature.tsv'
ser = serial.Serial(
  port='/dev/ttyUSB0',
   baudrate=9600,
sio = io.TextIOWrapper(
  io.BufferedRWPair(ser, ser, 1),
   encoding='ascii', newline='\r'
sio._CHUNK_SIZE =1
with open(outfile, 'a') as f: #appends to existing file
  while ser.isOpen():
      datastring = sio.readline()
      #\t is tab; \n is line separator
      f.write(datetime.utcnow().isoformat() + '\t' + datastring + '\n')
      f.flush() #included to force the system to write to disk
ser.close()
```

(see python/exercises/example\_code/ldfsp.py in your ncas-isc checkout)

## 2 Writing and Plotting NetCDF files Exercise

#### Exercise 7.

Write a function to convert the time as written in your datafile and return a Python datetime object.

p

#### Exercise 8.

Write a function to convert the temperature as written in your datafile and return a float in Kelvin.

$$T_K = T_C + 273.15$$

#### Exercise 9.

Read your datafile into Python using the csv module such that you end up with list object(s) containing floating-point temperature in K and timestamps as Python datetime objects.

see: https://docs.python.org/3/library/csv.html

#### Exercise 10.

- Create a Dataset (use the format NETCDF4\_CLASSIC)
- Convert your time series to a suitable CF-compliant series
- Create a suitable Dimension for your time series
- Create Variable objects for Temp and Time using appropriate units etc.
- Assign appropriate metadata to the Temp Variable and and the Dataset
- Add your time series and temp values to the Dataset
- Close and write your Dataset. Test that it parses correctly with ncdump

#### **Bonus Exercise 11.**

You can do a quick-and-dirty plot with ncview:

```
ncview sensor_data.nc
```

This isn't publication quality. Produce a line plot of temperature vs time using matplotlib and reading the data from your NetCDF file.

#### Bonus Exercise 12.

"CIS is an open source command-line tool for easy collocation, visualization, analysis, and comparison of diverse gridded and ungridded datasets used in the atmospheric sciences" It is based on python. Homepage: http://www.cistools.net/

```
cis plot temp:sensor_data.nc --xaxis time --yaxis temp \
    --title "Papouch Thermometer Data, 2017-02-22, UoL PRD" --xstep "0.010416" \
    --output sensor_data_sample.svg
```

Experiment with CIS.

#### Solution 7.

```
def convert_time(tm):
    tm = datetime.strptime(tm, "%Y-%m-%dT%H:%M:%S.%f")
    return tm
```

strptime is the opposite of strftime that we used earlier.

#### Solution 8.

```
def convert_temp(temp):
    value = temp.strip("+").strip("C").lstrip("0")
    return float(value) + 273.15
```

#### Solution 9.

```
infile='sample-serial-temperature-2h.tsv' #Or whatever your infile is called
outfile='sensor-data.nc'
from csv import reader

# Parse the data into python lists
times = []
temps = []

#open infile and read data into lists
with open(infile, 'rb') as tsvfile:
    tsvreader = reader(tsvfile, delimiter='\t')
    for row in tsvreader:
        times.append(convert_time(row[0]))
        temps.append(convert_temp(row[1]))
```

#### Solution 10.

See: python/exercises/example\_code/write\_sensor\_data\_to\_netcdf.py in your ncas-isc checkout.

#### Solution 11.

See: python/exercises/example\_code/plot-netcdf.py

#### Solution 12.

See: python/presentations/logging-data-from-serial-ports/sensor\_data\_sample.svg