

Backend Issue

- The chatbot session not found issue was due to the command

```
sudo nohup .venv/bin/python3 -m uvicorn main:app --host 0.0.0.0 --port 5400  
--workers 2 >> ~/app_output.log 2>&1 &
```

- **Issues**

- nohup command does not activate the complete venv required by the application to function. It just refers to the python3 bin present.
- The uvicorn command spawns 2 workers with the --workers 2 flag. But the 2 workers are unaware of context of each other.
 - If start-chat api call is received by the worker 1, worker 2 has no idea about the chat created and vice-versa.
 - If worker 2 received the continue-chat api call. It'll throw an Session Not Found error which was the issue all along, because it has no context of the chat created by the worker 1.
 - Thus sending the message multiple times worked sometimes because one of those calls was received by the worker 1 which created the chat and thus responded correctly.

FastApi Backend Deployment

- In the project directory which is to be deployed
 - Create a start.sh bash file with contents

```
#!/bin/bash  
  
PROJECT_DIR="<directory to the project>"  
VENV_DIR="$PROJECT_DIR/.venv"  
PORT=5400  
  
cd "$PROJECT_DIR" || exit  
  
echo "starting the server..."  
echo "PORT is $PORT"  
  
source "$VENV_DIR/bin/activate"  
  
uvicorn main:app --host 0.0.0.0 --port $PORT  
  
deactivate
```

- Change the PROJECT_DIR to the appropriate directory of the project.
- Remember to create a .venv inside the project directory which has all the dependencies the project needs.

- make the file executable using

```
chmod +x start.sh
```

Creating systemd unit file.

- This file will be used to start the server in the background and restart on reboot.
- Change the working directory to /etc/systemd/system
- Create a file called auxo_daa_backend.service with contents

```
[Unit]
Description=Chatbot Backend Auxo_DAA
After=network.target

[Service]
User=ubuntu
ExecStart=/home/ubuntu/Auxo_DAA_Backend/start.sh
WorkingDirectory=/home/ubuntu/Auxo_DAA_Backend
Restart=always

[Install]
WantedBy=default.target
```

- This file executes the start.sh created earlier.

Starting The Server

- Run this to start the server in the background

```
sudo systemctl start auxo_daa_backend.service
```

Auto-Starting The Server On Reboot

- Run this to enable auto-start the server on reboot

```
sudo systemctl enable auxo_daa_backend.service
```

Stop The Server

```
sudo systemctl stop auxo_daa_backend.service
```

Disable The Server

```
sudo systemctl disable auxo_daa_backend.service
```