# The WIT Developer's Handbook:

# A Reference Manual for the Development and Maintenance of Watson Implosion Technology

Robert Wittrock
Department of Business Analytics and Mathematical Science
IBM T.J. Watson Research Center
P.O. Box 218
Yorktown Heights, NY 10598

February 28, 2013

This document is available on GSA at:

{yktgsa}/projects/w/wit/doc/wit-dh/wit-dh.pdf

# **Table of Contents**

1.	Introduction	3
2.	The WIT-Projects Stream	
3.	What is MCL?	6
4.	How to Build MCL	
5.	How to Test MCL	10
6.	How to Build WIT	11
7.	How to Test WIT: The API Test	15
8.	How to Test WIT: If the API Test is Unsuccessful	17
9.	How to Add to the API Test	19
10.	How to Test WIT: The Thread Test	21
11.	How to Test WIT: The No-CPLEX Test	23
12.	How to Test WIT: The Stand-Alone Test	25
13.	How to Test WIT: If the Stand-Alone Test is Unsuccessful	28
14.	How to Add to the Stand-Alone Test	29
15.	How to Build and Test WIT-J	31
16.	How to Access Old Versions of the Code	32
17.	How to Update the WIT Guide	33
18.	A Walk Through the Makefiles	35
19.	Conventions of the WIT Source Code	38
20.	Structural Concepts	39
21.	A Structural Overview of WIT	40
22.	How to Add a Message to WIT	
23.	How to Add an Attribute to WIT	48
24.	How to Add an Attribute to WIT-J	57
25.	How to Add/Remove/Rename Source Files	
26.	How to Update the Copyright Dates	59
	References	62

## 1. Introduction

This is a document about WIT: Watson Implosion Technology. Its target audience is a "WIT developer": a person whose has responsibility for the on-going development and maintenance of WIT. The purpose of this document is to provide the information that would be essential for someone to do a proper job of developing and maintaining WIT, at least at a rudimentary level.

This document covers the following three software libraries, which together comprise the WIT asset:

- MCL
- WIT
- WIT-J

The greatest emphasis will be given to WIT itself.

As you can see from the Table of Contents, most of the sections of this document are devoted to "How to"s: explanations of how to perform various important well-defined tasks: building code, testing code, making certain kinds of revisions to the code. The remaining sections generally give overviews of various aspects of the WIT asset. Deep algorithmic explanations are not given.

## Prerequisite Knowledge:

This document assumes that the reader is already familiar with WIT from the point of view of a WIT application programmer. Specifically, the following knowledge is assumed:

- WIT concepts and capabilities. See [WIT Intro] and [WIT Guide].
- The WIT API. See [WIT Guide].
- WIT-J. See [WIT-J Guide].
- RTC (Rational Team Concert) and the WIT-Projects stream. See [RTC Intro].

#### Size of the Code

It may be helpful to be aware of the scale of the source code discussed by this document:

Table 1: Lines of Source Code

Library	Main Code	Test Code	Total Code
MCL	5K	1K	6K
WIT	142K	11K	153K
WIT-J	27K	7K	34K
Total	174K	19K	193K

## 2. The WIT-Projects Stream

The source code, test data, scripts, etc. for MCL, WIT, and WIT-J are all stored in the WIT-Projects stream on RTC. (See [RTC Intro] for how to work with the WIT-projects stream.) Thus, before working with the MCL, WIT, and WIT-J code, it would be helpful to have a high-level understanding the contents of the WIT-Projects stream.

If you load the entire WIT-Projects stream into a local workspace, these are the directories you get:

- config
- eso2
- mcl
- samples
- sce
- scenario
- wit
- witj
- witm
- wit-sa-test
- witutil
- witviz

The contents of these directories are as follows:

The config directory contains a collection of files that are used (via include statements) by the makefiles for building the various libraries and executables in the WIT-Projects stream. You'll need the config directory pretty much any time you use "make" to build something in the WIT-Projects stream.

The mcl directory contains MCL.

The wit directory contains WIT.

The wit-sa-test directory contains the Stand-Alone Test for WIT.

The witj directory contains WIT-J.

The remaining directories contain source code, etc. for software that is not covered by this document:

The samples directory contains a collection of small example WIT application programs.

The sce, witutil, and scenario directories contain SCE and the WitUtil and Scenario libraries. SCE ("Supply Capability Engine") is a major WIT application program developed by Tom Ervolina, which adapts and extends WIT's capabilities to the specific needs of IBM's hardware supply chain. The WitUtil and Scenario libraries are used by SCE and are WIT applications themselves.

The eso2 directory contains ESO2. ESO2 ("Economic Supply Opportunity", second implementation) is a WIT application program for reverse logistics (product disassembly planning) developed by JP Fasano. As of Nov. 2012, it was still being used by the IBM Integrated Supply Chain organization in Montpellier, France, but it isn't really being supported, because JP is no longer with IBM.

The witviz directory contains WitViz, a visualization tool for WIT models developed by Donna Gresh and implemented as a WIT-J application program.

The witm directory contains WIT-M, a Java class library developed by me that facilitates the construction and manipulation of WIT models by providing modeling language-like constructs to be used by a WIT-J application program.

## 3. What is MCL?

As a WIT application programmer, you might not know what MCL is. MCL ("Message Class Library") is a library of C++ classes whose purpose is to make it easy for a program to create, manage, and issue "messages": textual output. It was created in the late 90s by members of the WIT team: designed by JP Fasano, myself, and Weiwen Zhao, and initially implemented by Weiwen. We originally intended for it to be used by as many software tools as possible, but in fact it was only used by two: WIT and SCE.

MCL is considered to be part of the WIT asset and is maintained along with the WIT code. For example, if WIT is to be ported to a new platform, then MCL must also be ported to that platform and it must be ported before WIT. Unlike WIT, the MCL code has been stable for a long time: Changes are made to it are infrequently and usually just for porting purposes.

Relationship to other WIT software:

- WIT depends on MCL, directly.
- SCE depends on MCL, directly.

MCL does not depend on WIT or SCE.

#### 4. How to Build MCL

MCL can be built on the following platforms:

- Linux, 32 bit (Red Hat and Ubuntu).
- z/Linux, 64 bit.
- AIX, 64 bit.
- Windows.

The Linux, z/Linux, and AIX platforms are all similar to Unix. They are called the "Unix-like platforms" in this document.

The port of MCL to Windows uses a special platform that we worked out, called "Windows SDK", which is a hybrid two distinct sets of software development tools: the Microsoft Windows SDK and the GNU MSYS environment. For an explanation of how to build MCL on the Windows SDK platform, see [Win SDK].

#### How to Build MCL on Linux, 32 Bit

First, you need to load the following directories from the RTC WIT-Projects stream (See [RTC intro] for how to do this.):

- · config
- mcl

Next, you need to set up some environment variables. You normally specify these in your login profile, in my case, ~/.bash profile. The first environment variable to set is:

```
WIT HOME
```

This is the pathname of the directory where your RTC local workspace for the WIT-Projects stream is located. For example, the MCL source code would be located at \$WIT HOME/mcl/src. In my case, I have it set as:

```
export WIT HOME=/home/rjw/main/wit/wit-projects
```

The next environment variable to set is:

```
PLATFORM
```

This is the "platform ID" that we have defined for each platform on which we can build WIT-related software. In this case, the correct value is linux:

```
export PLATFORM=linux
```

Next, you select an <code>exe\_type</code> exe\_type is a makefile variable used by all of the makefiles in our WIT-Projects directory. It specifies which kind of build is being requested by a make command. (I think <code>exe\_type</code> means "executable type"). There are 4 allowed values for <code>exe\_type</code>:

- debug
  - Generates "debug" code: code that can be processed by a debugger.
  - Does run-time error checking: asserts, array indexes, etc.
  - This is the exe type normally used for developing and testing the code.

- released
  - Generates optimized code.
  - This is the exe\_type that's to be used for released/production code, especially code that's to be deployed externally.
- fast
  - Generates optimized code.
  - o In the case of MCL, this is the same as released. (In the case of WIT, there's a distinction.)
- profile
  - Generates profileable code, code that be processed by a profiler.

Next, you CD to the build directory for MCL on Linux:

```
cd $WIT_HOME/mcl/linux
```

Next, you issue the "make" command, e.g.:

```
make exe type=debug all
```

#### Notes:

- You can use any exe type.
- The "all" target builds the MCL Unit Tester, which also causes the MCL library to be built.
- Alternatively, you can use the "unitTest" target.
- To build the MCL library without the Unit Tester, use the "libmcl.a" target.
- You can use the -j [N] argument to get N asynchronous compiles. This is a faster build, if your machine has more than one core. For example:

```
make exe_type=debug -j4 all
```

Before building MCL, it might be a good idea to issue the following from the MCL build directory:

```
make clean
```

This removes all object, library, and executable files for MCL on this platform, so that you can be sure that they will not contribute to the current build.

Sometimes it's necessary to issue the following (from the MCL build directory) before building MCL:

```
make depend
```

This updates the list of source code dependencies that will be used by make when building MCL. Specifically, it revises the MCL makefile, \$WIT\_HOME/mcl/linux/Makefile, replacing its dependency list with a new one, based on the #include statements that it finds by analyzing the MCL source code. The dependency list is the part of the makefile that begins after the following line:

```
# DO NOT DELETE THIS LINE -- make depend depends on it.
```

and continues to the end of the file.

Generally you only need to issue make depend when a change is made to the MCL source code (which is rare).

# How to Build MCL on z/Linux, 64 Bit

This is almost the same as the Linux case, but with the following differences:

- export PLATFORM=zlinux64
- cd \$WIT\_HOME/mcl/zlinux64

## How to Build MCL on AIX, 64 Bit

This is almost the same as the Linux case, but with the following differences:

- export PLATFORM=power64v5
- cd \$WIT HOME/mcl/power64v5

## 5. How to Test MCL

The MCL Test is implemented on all of our platforms: Linux, z/Linux, AIX, and Windows SDK. It should be used under the following circumstances:

- If you are upgrading to a new compiler level or a new environment of some kind, you need to perform the test on that platform.
- If you change any MCL code, you need to perform the test on all platforms.

The procedure is as follows:

First, you build the MCL unitTest executable with exe type=debug. (See Section 4.)

- The debug exe\_type is used so that asserts will be activated for the test.
- On Windows SDK, the unitTest executable is called unitTest.exe.

Next, run the unitTest executable:

• cd \$WIT HOME/mcl/\$PLATFORM

(You're probably already there from the build.)

• ./unitTest

Normally, the test will produce a large amount of output, most of which will fly off the screen, concluding with the following line:

```
All tests completed successfully.
```

If it terminates with that line, the test is successful; if it terminates any other way, it's unsuccessful.

#### If the test is unsuccessful

The MCL unit test mostly consists of many test outputs that are compared with expected output. If the comparison fails, the program terminates with a message showing what was different. That message can then be used as the starting point of an investigation into the underlying problem.

## 6. How to Build WIT

Like MCL, WIT can be built on the following platforms:

- Linux, 32 bit (Red Hat and Ubuntu).
- z/Linux, 64 bit.
- AIX, 64 bit.
- Windows SDK

For an explanation of how to build WIT on the Windows SDK platform, see [Win SDK].

#### How to Build WIT on Linux, 32 Bit

First, you need to load the following directories from the RTC WIT-Projects stream:

- · config
- mcl
- wit

Next, you build MCL. (See Section 4.)

For WIT, you keep the environment variables <code>WIT\_HOME</code> and <code>PLATFORM</code> as they were for MCL. In addition, there are three more environment variables that apply only to WIT: <code>WIT\_CPLEX\_HOME</code>, <code>WIT\_CPLEX\_HOME</code>, <code>WIT\_CPLEX\_LIB\_SUBDIR</code>, and <code>WIT\_GEN\_PARSER</code>.

```
WIT CPLEX HOME.
```

If CPLEX is to be embedded into WIT, WIT\_CPLEX\_HOME should be defined as the path where CPLEX files are located. In particular, cplex.h should be located at:

```
$WIT CPLEX HOME/include/ilcplex/cplex.h
```

If CPLEX is not to be embedded into WIT, WIT\_CPLEX\_HOME should be left undefined, or defined as the null string.

```
WIT CPLEX LIB SUBDIR
```

Normally, the makefiles know where to look for the CPLEX library (based on WIT\_CPLEX\_HOME and the platform). But in some cases, it is necessary to override the default location used by the makefile and specify a different location. To do so, set WIT\_CPLEX\_LIB\_SUBDIR to the subdirectory where the CPLEX library is located, so that its full path name is given by:

```
$WIT CPLEX HOME/lib/$WIT CPLEX LIB SUBDIR/libcplex.a
```

Otherwise, leave this variable unset and the makefile will use its default location for the CPLEX library.

```
WIT GEN PARSER
```

In order to read WIT data files, WIT makes use of a pair of language processing utilities called Flex and Bison. (modern versions of Lex and Yacc). To be precise, Flex and Bison are not invoked when WIT is reading a WIT data file; instead, they are invoked by the WIT makefile, when WIT is being compiled. Flex and Bison read in a set of input files that define a language and then output C or C++ source code that "parses" the language. The resulting C/C++ source code is called a "parser": it reads a file in the defined language and executes the actions specified in the file according to the language.

In WIT's case, the input to Flex and Bison is the following two files:

- witLexer.l (input to Flex)
- witParse.y (input to Bison).

These two files are part of WIT's modifiable source code: the developer is free to alter them as needed. The output of Flex and Bison are the following three "parser" files:

- witLexer.C (generated by Flex)
- ytab.h (generated by Bison).
- witParse.C (generated by Bison).

The parser files constitute WIT's generated source code: the developer must never alter them manually. All five of these files are located in the \$WIT HOME/wit/src directory.

The makefile calls Flex and Bison to generate the parser files according to the usual rules of the make utility, i.e., whenever the input files have a newer time stamp than the output files, subject to the following two restrictions:

- They are only generated on the "linux" platform. This allows us to avoid dealing with the various different versions of Flex and Bison that are out there. The files generated on Linux are used on all platforms. Note that this arrangement implies that the input files, witlexer.1 and witParse.y should only be modified on the Linux platform. If you modify them on any other platform, the parser files will not get regenerated and WIT's behavior will not reflect your changes.
- They are only generated, if the environment variable WIT\_GEN\_PARSER is set to YES. If WIT is being built on Linux by a WIT application programmer, there is no need to regenerate the parser files, so by default, they are not generated. This default behavior occurs if WIT\_GEN\_PARSER is left unset. If you are developing/maintaining WIT, then on Linux, you should set WIT GEN\_PARSER:

```
export WIT GEN PARSER=YES
```

The parser generation makefile logic is located in: \$WIT HOME/wit/linux/Makefile.

Next, you select an exe\_type from the valid possibilities: debug, released, fast, or profile. These have the same properties as in the MCL case, but with one additional aspect that applies only to WIT: If exe\_type=debug, fast, or profile, the resulting code is considered to be built in "development mode". When WIT is in development mode, the following two undocumented aspects of WIT are enabled:

- The stand-alone executable has a set of "development control parameters", i.e., control parameters that are recognized only in development mode.
- There is an API function, witInterpretDevCmd, that only accepts invocations in development mode.

WIT's development mode has the following purposes:

- It gives the WIT developer access to WIT capabilities that are not needed by or desirable for application programmers, and therefore avoids the need for user documentation, rigorous testing, etc. These development capabilities are mostly debugging and testing capabilities. Most of WIT's stand-alone executable tests (described later in this document) use development control parameters.
- It allows the WIT developer the ability to add new partially implemented capabilities to WIT, while keeping them unavailable in production builds of WIT. This is done by requiring the use of a special development control parameter or a special call to witInterpretDevCmd before the new capability can

be invoked. I use this technique virtually every time I add a new capability to WIT.

The purpose of exe type=fast is to create a code-optimized development build of WIT.

Normally, exe type should be set to the same value for MCL and WIT.

Next you CD to the build directory for WIT on Linux:

```
cd $WIT_HOME/wit/linux
```

Next, you issue the "make" command, e.g.:

```
make exe type=debug all
```

#### Notes:

- You can use any exe type.
- The "all" target builds the WIT Stand-Alone Executable, which also causes the WIT library to be built.
- Alternatively, you can use the "wit" target.
- To build the WIT library without the Stand-Alone Executable, use the "libwit.a" target.
- You can use the -j [N] argument to get N asynchronous compiles. This is a faster build, if your machine has more than one core. For example:

```
make exe type=debug -j4 all
```

As with MCL, before building WIT, it might be a good idea to issue the following from the WIT build directory:

```
make clean
```

This removes all object, library, and executable files for WIT on this platform, so that you can be sure that they will not contribute to the current build.

As with MCL, it's also sometimes necessary to issue the following before building WIT, to update the list of source code dependencies that will be used by make when building WIT:

```
make depend
```

Generally you only need to issue make depend when a change is made to the WIT source code.

#### How to Build WIT on z/Linux, 64 Bit

This is almost the same as the Linux case, but with the following differences:

- export PLATFORM=zlinux64
- cd \$WIT HOME/wit/zlinux64
- WIT GEN PARSER has no effect.

# How to Build WIT on AIX, 64 Bit

This is almost the same as the Linux case, but with the following differences:

- export PLATFORM=power64v5
- cd \$WIT\_HOME/wit/power64v5
- WIT GEN PARSER has no effect.

## 7. How to Test WIT: The API Test

There are four procedures for testing WIT:

- The API Test: A general test of WIT; uses the API.
- The Thread Test: A test of WIT's thread-safety features; uses the API.
- The No-CPLEX Test: A test of WIT without CPLEX embedded; uses the API.
- The Stand-Alone Test: A test of WIT's various capabilities; uses the Stand-Alone Executable.

This section will describe the API Test.

The WIT API test is implemented on all of our platforms: Linux, z/Linux, AIX, and Windows SDK. It should be used under the following circumstances:

- If you are upgrading to a new compiler level or a new environment of some kind, you need to perform the test on that platform.
- If you upgrade either of the prerequisites to WIT (MCL or CPLEX), you need to perform the test on all platforms.
- If you change the WIT code or the API Test code, you need to perform the test on all platforms.

The procedure is as follows:

First, you must add the following directory to your PATH:

```
$WIT HOME/wit/scripts
```

The script for the API test is in this directory and it invokes other scripts in this directory.

Next, you build WIT with exe type=debug. (See Section 6.)

• The debug exe type is used so that asserts and other error checking will be activated for the test.

Next, you invoke the WIT API test script:

```
wit-api-test
```

This script builds and runs the following four WIT application programs:

- apiAll Invokes each of WIT's API functions at least once.
- msgAll Causes each of WIT's "testable" messages to be issued.
- extOptTest Tests the external optimizing implosion capability.
- errTest Tests WIT's response to various error conditions.

The source code and data for this test (as well as the outputs of it) are stored in the following directory:

```
$WIT HOME/wit/api-test
```

The script prints a few high-level progress indicators to the screen (like "Running apiAll"), but directs most of its output to the following file:

```
$WIT HOME/wit/api-test/api-out-new.txt
```

The script then runs a filtered diff, comparing this file against the following file (acquired from the WIT-Projects stream):

```
$WIT HOME/wit/api-test/api-out-$PLATFORM.txt
```

For example, api-out-linux.txt. This comparison file is platform-specific, because there are many minor differences in the output on different platforms, due to different floating point representations.

The diff output is stored as:

```
$WIT HOME/wit/api-test/api-out-diff.txt
```

If the diff file is empty, the script will print the following lines and terminate:

```
No Significant differences were found.
```

```
The WIT API test was successful.
```

If it terminates with those lines, the test is successful.

If the diff file is not empty, then the test is unsuccessful and the script terminates with the following lines:

```
Significant differences were found. See:
```

```
$WIT HOME/wit/api-test/api-out-diff.txt
```

The WIT API test was unsuccessful.

where \$WIT HOME is expanded to its value.

#### 8. How to Test WIT: If the API Test is Unsuccessful

If the WIT API test is unsuccessful, the first thing you need to do is to perform the other WIT tests for further insight. But for now, let's consider what needs to be done with respect to the API test.

You basically need to look at the api-out-diff file, the api-out-new file and the api-out-\$PLATFORM file and figure out what the problem is. Doing that, of course, requires a true understanding of how WIT works, which is beyond the scope of this section. Anyway, once you have determined the exact nature of the problem, there are essentially three kinds of actions to take:

- 1. You might decide that the new output is correct and should become the new basis of comparison. Perhaps you changed the code and the new output is just what you expected. In this case, you need to save the new output on all platforms. To save the new output on the current platform, you take the following steps:
  - Remove the api-out-\$PLATFORM.txt file.
  - Rename (i.e., mv) the api-out-new.txt file to api-out-\$PLATFORM.txt.
  - Rerun the API test.
    - The test should be successful.
  - Check-in and deliver the revised api-out-\$PLATFORM.txt file to the WIT-Projects stream.
    - Note that RTC will ignore (not check in) api-out-new.txt and api-out-diff.txt. This is specified in the file \$WIT HOME/wit/.jazzignore.

Then you need to run the API test on each of the other platforms and (assuming it makes sense) save the new output on each platform.

2. You might decide that the new output is correct, but is too variable to be used as the basis of comparison. For example, it might involve a run time. In this case, you need to add to the filter in the "diff" command that's in the wit-api-test script, so that the unavoidable differences will be ignored. This is the current diff command in the script:

```
diff
  -I "^Build Date:"
  -I "^Run Started At:"
  -I "^
        Build Date:"
 -I "^
              Run Started At:"
 -I "^Elapsed real time ="
  -I "^ Real time
  -I "^Total (root+branch&cut) ="
  -I "^Total crossover time ="
  -I "^Total time on"
  -I "^Barrier time ="
  -I "^Presolve time ="
  -I "^Found feasible solution after"
  -I "^Total time for automatic ordering ="
  -I "^Root relaxation solution time ="
  api-out-$PLATFORM.txt
  api-out-new.txt
 > api-out-diff.txt
```

The -I lines are the filter. See documentation on the diff command for how use the -I option.

Then you'll need to take these steps:

- Rerun the API test.
  - Get a successful result.
- Check-in and deliver the revised script.
- Run the API test on the other platforms.
- 3. You might decide that the new output is incorrect. In this case:
  - Revise the WIT source code and/or the API test source code as needed.
  - Rerun the API test.
    - Get a successful result.
  - o If WIT code was changed, run other WIT tests as appropriate.
  - Check-in and deliver the revised code.
  - Run the appropriate WIT tests on the other platforms.

Of course, you may have a combination of the above cases and therefore need to do a combination of the corresponding actions. (Case 3 is likely to require saving the new output.)

## 9. How to Add to the API Test

Normally when you add new functionality to WIT, you also need to add new tests. This section will explain how to add new tests to the API Test.

- apiAll:
  - Since this program is supposed to invoke each of WIT's API functions at least once, you need to revise apiAll any time you add a new API function. Here are some suggestions for how to do this:
    - It's probably a good idea to find something similar in apiAll and use it as an example.
    - If your new functionality involves more than one API function, it's best to collect them together in one or more functions that implement a small use case for the new capability.
    - Generally, you'll want the test to produce some indicative output so that if something changes, the change has a chance to show up in the diff output.
    - Note that if you add a call to witOptImplode or witStochImplode to apiAll, the call must be conditional on the value of the cplexEmbedded attribute. The apiAll code retrieves the value of this attribute from WIT and stores it in a global variable, cplexEmbedded.
- msqAll:
  - This is explained in section Error: Reference source not found.
- extOptTest:
  - You probably won't need to add to this test.
- errTest:
  - The purpose of errTest is to test WIT's response to error conditions that cannot be produced running the Stand-Alone Executable.
  - Note that each error test case is implemented as a separate invocation of the errTest program, because the errors being tested normally cause the program to terminate.
  - To add a new case to errTest, perform the following steps:
    - Determine the index of the test case: N, where N-1 is the highest test case index that already exists. For example N=72.
    - Add a test case function, called testCase{N}, e.g., testCase72.
    - You can use other testCase functions as examples.
    - Usually the testCase function will end with a call to terminationExpected, which prints
      a special error message if it is called. Normally the execution of a testCase function will not
      reach its last line, because WIT will terminate with an error message when it detects the error
      that's being tested. The call to terminationExpected prints the appropriate error message if
      that goes wrong and the last line is reached.
    - The errTest program accepts a single string argument whose value is the index of the text case being requested. The main program contains a long if-then-else chain to call the requested test case function. You need to add an "else if" clause to this if-then-else chain, calling your test case function. For example:

```
else if (theArg == "72")
  testCase72 ();
```

- The if-then-else chain concludes with an error message indicating the largest test case index allowed. You need to increase the index that it prints.
- Finally, add a call to errTest to the wit-api-test script in \$WIT\_HOME/wit/scripts, passing your test case index as the argument. For example:

## 10. How to Test WIT: The Thread Test

The WIT Thread Test is a test of WIT's thread safety features. It is implemented on the Linux platform only. It should be used under the following circumstances:

- If you are upgrading to a new compiler level or a new environment of some kind on Linux, you need to perform the test.
- If you make changes to any of the following code, you need to perform the test:
  - The WIT thread-safety code (obviously).
  - The thread test code (obviously).
  - A non-routine change to the WIT API code.
- If you alter the code in a way that is expected to alter the output of WIT, you'll need to perform the test so that you can revise the expected output, if necessary.
- If you want an especially thorough test of WIT, you can perform the test for that purpose.

The procedure is as follows:

First, you need to have Java installed on your machine. The IBM version of Java is available from IBM's Java Information Manager:

```
http://w3.hursley.ibm.com/java/jim/
```

Next, you set the JAVA\_HOME environment variable to the full path name of the directory in which Java is located. For example, my login profile script contains the following line:

```
export JAVA HOME=/opt/ibm/java-i386-60
```

Specifically, JAVA\_HOME should be set so that the programs "javac", "jar", and "java" are located under \$JAVA HOME/bin and the C++ header file "jni.h" is located under \$JAVA HOME/include.

Next, as with the API test, the following directory must be in your PATH:

```
$WIT HOME/wit/scripts
```

Next, you build WIT with exe type=debug (if you haven't already).

Next, you invoke the WIT Thread Test script:

```
wit-thread-test
```

This script builds and runs (several times) a Java program called "ThreadTester", which creates a second Thread. The two Threads call native methods whose C++ implementations make API calls to WIT. These WIT API invocations are therefore asynchronous and are designed to test WIT's thread-safety features.

The source code and data for this test (as well as the outputs of it) are stored in the following directory:

```
$WIT HOME/wit/thread-test
```

The script directs most of its output to the following file:

```
$WIT HOME/wit/thread-test/thread-out-new.txt
```

The script then runs a filtered diff, comparing this file against the following file:

```
$WIT HOME/wit/thread-test/thread-out-linux.txt
```

The diff output is stored as:

```
$WIT HOME/wit/thread-test/thread-out-diff.txt
```

When the script is finished, it does not actually indicate whether or not the test was successful: You must determine this yourself, by examining the thread-out-diff.txt file. This diff output file will almost never be empty: Due to the asynchronous nature of its WIT API invocations, the individual lines of output will usually appear in a different order each time you run the test.

If the diff output contains only the following kinds of lines, you can consider the test to be a successful:

- Lines that indicate the same output in a different order: Specifically, a line beginning with ">" that is otherwise identical to another line beginning with "<".
- Unmatched lines reporting normal WIT behavior. These indicate that one of the threads was terminated earlier or later in the new run than it was in the saved run. A successful test may have a few of these, e.g.:

```
< WIT0668I Heuristic allocation is now active.
```

If the diff output contains unmatched lines that are reporting an error, the test is unsuccessful.

#### If the Thread Test Is Unsuccessful

The procedure in this case is similar to the procedure for the API test, except that it only applies on Linux and you're working in the thread-test directory.

#### How to Add to the Thread Test

You probably won't need to do this.

## 11. How to Test WIT: The No-CPLEX Test

The WIT No-CPLEX Test is a test of WIT without CPLEX embedded, using the API. Its purpose is to guard against the (unlikely) event that the code has somehow been changed in such a way that it works OK when CPLEX is embedded, but fails when CPLEX is not embedded. It is implemented on the Linux platform only. It should be used under the following circumstances:

- If you alter any WIT code that is conditional on whether or not CPLEX is embedded into WIT, you need to perform the test.
- If you alter the code in a way that is expected to alter the output of WIT, you'll need to perform the test so that you can revise the expected output, if necessary.
- If you alter the apiAll code, you'll need to perform the test so that you can revise the expected output, if necessary.
- If you want an especially thorough test of WIT, you can perform the test for that purpose.

The procedure is as follows:

First, as with the API test, the following directory must be in your PATH:

```
$WIT HOME/wit/scripts
```

Next, you rebuild WIT on Linux with exe type=debug, but without CPLEX embedded:

- export WIT CPLEX HOME=
- cd \$WIT HOME/wit/linux
- rm CplexMgr.o
  - Alternatively: make clean
- make exe type=debug all

Note that CplexMgr.C is the only source file in WIT that is compiled differently by the makefile depending on the value of WIT CPLEX HOME.

Next, you invoke the WIT No-CPLEX Test script:

```
wit-no-cplex-test
```

This script builds and runs <code>apiAll</code>. The <code>apiAll</code> program has many places where the code takes different action depending on whether or not CPLEX is embedded into the WIT library that it's using. (It uses WIT's global "cplexEmbedded" attribute for this purpose.) In this way, it is able to perform meaningful tests both with and without CPLEX.

The source code and data for this test (as well as the outputs of it) are stored in the following directory:

```
$WIT HOME/wit/api-test
```

The script directs most of its output to the following file:

```
$WIT HOME/wit/api-test/no-cplex-out-new.txt
```

The script then runs a filtered diff, comparing this file against the following file:

```
$WIT HOME/wit/api-test/no-cplex-out-linux.txt
```

The diff output is stored as:

```
$WIT HOME/wit/api-test/no-cplex-out-diff.txt
```

If the diff file is empty, the script will print the following lines and terminate:

```
No Significant differences were found.

The WIT No-CPLEX test was successful.
```

If it terminates with those lines, the test is successful.

If the diff file is not empty, then the test is unsuccessful and the script terminates with the following lines:

```
Significant differences were found. See:

$WIT_HOME/wit/api-test/no-cplex-out-diff.txt

The WIT No-CPLEX test was unsuccessful.
```

After completing a successful No-CPLEX Test, you should restore WIT to a CPLEX-embedded build:

- export WIT CPLEX HOME={Whatever}
- cd \$WIT HOME/wit/linux
- rm CplexMqr.o
- make exe type=debug all

## If the No-CPLEX Test Is Unsuccessful

The procedure in this case is similar to the procedure for the API test, except that it only applies on Linux.

## How to Add to the No-CPLEX Test

Since the No-CPLEX test is based on apiAll, it gets revised whenever apiAll is revised. There's no need to do anything beyond this.

## 12. How to Test WIT: The Stand-Alone Test

The WIT Stand-Alone Test is a procedure that performs a very detailed test of WIT's capabilities by running the Stand-Alone Executable many times. It is implemented on the Linux platform only. It should be used under the following circumstances:

- If you are upgrading to a new compiler level or a new environment of some kind on Linux, you need to perform the test.
- If you upgrade either of the prerequisites to WIT (MCL or CPLEX), you need to perform the test.
- If you change WIT code, you need to perform the test.

The procedure is as follows:

First, in addition to the directories you need for WIT, you need to load the wit-sa-test directory from the WIT-Projects stream. The wit-sa-test directory contains the following three top-level directories:

- data Contains the WIT input data files for the Stand-Alone Test, along with the corresponding saved output files.
- params Contains the control parameter files for the Stand-Alone Test.
- scripts Contains the scripts for the Stand-Alone Test.

Most of the input data files in the data directory were created by hand (by me) in order to test various aspects of WIT's capabilities as I was implementing them. The rest of them were contributed by the developers of WIT's main applications (GIView/Scorpio, SCE, ESO2), often documenting bugs that were subsequently fixed.

Next, you must add the following directory to your PATH:

```
$WIT HOME/wit-sa-test/scripts
```

Next, you build the WIT Stand-Alone Executable with exe type=debug (if you haven't already).

Next, you invoke the WIT Stand-Alone Test script:

```
wit-test-all
```

This script invokes a series of other scripts, each of which tests a different one of WIT's capabilities. For example, wit-test-multi-route tests the Multi-Route capability. As of this writing, wit-test-all invokes 28 different capability test scripts.

Each capability test script makes numerous calls to the script wit-test-case. This script performs a test of an individual test case for the capability. As of this writing, the Stand-Alone Test performs 707 individual case tests.

There are three arguments to the wit-test-case script:

- \$1 This is the subdirectory of \$WIT\_HOME/wit-sa-test/data in which the input data file for the test case is to be found. The file name is always wit.data.
- \$2 This the stem of the name of the parameters file.
- \$3 If this is empty or ≠ "save", the test will be run.

  If this is "save", the test will not be run; the results will be saved instead.

#### Consider for example:

```
wit-test-case multi-route/case02 heur-spl3
```

This invocation performs a case test using the following files as the input data file and control parameter file:

```
$WIT_HOME/wit-sa-test/data/multi-route/case02/wit.data
$WIT_HOME/wit-sa-test/params/heur-spl3.par
```

The output files for the case test are placed the following directory, created by the script:

```
$WIT HOME/wit-sa-test/data/$1/$2/output-new
```

For example:

```
$WIT_HOME/wit-sa-test/data/multi-route/case02/heur-spl3/output-new
```

After the script runs the Stand-Alone Executable, it then runs a script wit-test-case-diff that performs a filtered diff on the output files, using the following directory (loaded in from the WIT-Projects stream) as the basis of comparison:

```
$WIT HOME/wit-sa-test/data/$1/$2/output-sav
```

Specifically, each file in the output-sav directory is compared to the corresponding file in the output-new directory with a filtered diff.

#### How to Tell Whether or Not the Stand-Alone Test was Successful

The Stand-Alone Test is considered to be successful if and only if each of the capability tests is successful. A capability test is considered to be successful, if and only if each of the filtered diffs for each of its case tests produces an empty diff output.

Specifically, when a capability test begins, it prints (to stdout) a heading identifying the test, preceded and followed by a line of underscores. For example:

```
Test of Multi-Route
```

When a capability test is successful, that's all it prints. So when the Stand-Alone Test is successful, this is what it prints:

```
Test of Multi-Route

Test of NSTN Build-Ahead

Test of ASAP Build-Ahead

{25 more capability test headings...}
```

If a capability test is unsuccessful, at least one of its filtered diffs produces a non-empty output. When the output of a filtered diff (from a particular case test) is non-empty, the diff output is printed, preceded by a

heading indicating which files were being compared. For example, suppose a difference was found in file soln.out when running a test on nstn/case02/wit.data with parameter file heur-spl3.par. The script would print it as follows:

```
nstn/case02/heur-spl3/output-sav/soln.out
  nstn/case02/heur-spl3/output-new/soln.out
55c55
   0 7.000 10.000
<
    0 6.000 10.000
Here is an example of the output of an unsuccessful Stand-Alone Test:
Test of Multi-Route
Test of NSTN Build-Ahead
_____
  nstn/case02/heur-spl3/output-sav/soln.out
  nstn/case02/heur-spl3/output-new/soln.out
_____
55c55
   0 7.000 10.000
<
> 0 6.000 10.000
  nstn/case02/heur-spl3/output-sav/wit-log.txt
  nstn/case02/heur-spl3/output-new/wit-log.txt
_____
105c105
< Permanent Commit: Part C, Period O, Qty: 7.000
> Permanent Commit: Part C, Period 0, Qty: 6.000
Test of ASAP Build-Ahead
{25 more capability test headings...}
```

\_\_\_\_\_\_

This output indicates that the NSTN Build-Ahead Test was unsuccessful, with differences in two files. All other capability tests were successful.

## 13. How to Test WIT: If the Stand-Alone Test is Unsuccessful

If the output of the Stand-Alone Test script is large, you'll need to redirect it to a file, so you can work with it.

Usually the Stand-Alone Test will be unsuccessful only on a proper subset of the capability tests. It's generally helpful to rerun the failing capability tests individually so you can work with them one at a time. To find the names of the capability test scripts, look at the wit-test-all script. In the example of the previous section, you would rerun the wit-test-nstn script.

Then you would study the files that are flagged as different along with the corresponding input data file. In the above case, you'd study nstn/case02/wit.data and the resulting soln.out and wit-log.txt files in the output-sav and output-new directories.

As with the API test, once you have determined the exact nature of the problem, there are essentially three kinds of actions to take:

- 1. You might decide that the new output is correct and should become the new basis of comparison. In this case, you need to save the new output of the particular capability test in question. To save the output of a capability test, you take the following steps:
  - Run the capability test script with "save" as the argument, e.g.:

```
wit-test-nstn save
```

- This cleans up the output-new directory a bit and then renames it to output-sav.
- It does <u>not</u> run the test.
- Rerun the capability test, to get a successful result.
- Eventually, you will need to check-in and deliver the new output-sav directory to the WIT-Projects stream.
- To save the output of all of the capability tests, issue the following:

```
wit-test-all save
```

- 2. You might decide that the new output is correct, but is too variable to be used as the basis of comparison. In this case, you need to take these steps:
  - Add to the filter (the -I lines) in the "diff" command that's in the wit-test-case-diff script.
  - Rerun the capability test, to get a successful result
  - Eventually check-in and deliver the revised script.
- 3. You might decide that the new output is incorrect. In this case:
  - Revise the WIT source code and/or the input data file as needed.
  - Rerun the capability test, to get a successful result
  - Run all appropriate WIT tests.
  - Eventually check-in and deliver the revised code/data.

Of course, you may have a combination of the above cases and therefore need to take a combination of the corresponding actions.

## 14. How to Add to the Stand-Alone Test

The Stand-Alone Test is the place to test any new functionality that you add to WIT, as long as it's something that can be tested by running the Stand-Alone Executable, including both "positive" functionality and error checking. The essential advantage of using the Stand-Alone Executable for testing is clarity: Each test case is defined by a WIT data file and a parameters file, whereas API-based test cases are defined by source code.

As you know, the Stand-Alone Test consists of a series of capability tests, each of which consists of a series of series of individual test cases.

To add a test case to an existing capability test, perform the following steps:

• Usually, you will create a new data file for the case. As explained in section 12, the pathname for a data file in the Stand-Alone Test must be of the following form:

```
$WIT HOME/wit-sa-test/data/$1/wit.data
```

where \$1 is the value of the first argument to the wit-test-case script.

- Sometimes, you can use an existing data file, with a new parameters file.
- Usually, you can use an existing parameters file. Once again, these are located at:

```
$WIT HOME/wit-sa-test/params
```

- If none of the existing parameters files is appropriate for your test, create a new one.
  - In this case, copy the first two lines from an existing parameters file into your new one. These two
    lines set the log\_ofname and data\_ifname parameters to the values that are needed by the
    Stand-Alone Test scripts.
- Next, add an invocation of the wit-test-case script to the capability test script that you are working on, e.g.:

```
wit-test-case nstn/case21 heur-spl3 $1
```

- Copying and modifying an existing line in the capability test script is a good way to do his.
- Run the modified capability test script.
  - It will print an error message, indicating that your output-sav directory does not exist. You can ignore this error message for now.
- Look at the content of the files in the relevant output-new directory and verify that the output is what you want. If it is not, modify the input files and repeat these steps, as needed.
- When the output is correct, run the capability test script with "save" as the argument, e.g.:

```
wit-test-nstn save
```

• Run the capability test script again, the normal way. This time there should be no error message and no diff output.

If you are adding a whole new capability to WIT, you'll need to add a new capability test. To do this, perform the following steps:

• You'll probably need to add a new directory to the data directory, e.g.,

• Create a new capability test script, e.g.,

- The name of the script doesn't have to match the name of the directory, but it often does.
- It's probably best to copy and modify an existing capability test script.
- Add test cases to the new capability test script as needed, using the procedure given above.
- Add an invocation of the new capability test script to the Stand-Alone Test script, wit-test-all.
- Run the new wit-test-all.

#### 15. How to Build and Test WIT-J

The procedures for building and testing WIT-J are given in [WIT-J Set-Up]. Note that WIT-J is implemented on two of our platforms:

- Linux
- Windows SDK

The WIT-J tests should be used under the following circumstances:

- If you are upgrading to a new compiler level or a new environment of some kind on Linux or Windows, you need to perform the test on that platform.
- If you upgrade any of the prerequisites to WIT-J (MCL, CPLEX, or WIT), you need to perform the test on both platforms.
- If you change WIT-J code or WIT-J test code, you need to perform the test on both platforms.

See [WIT-J Set-Up] for how to perform the WIT-J test.

#### If the WIT-J Test is Unsuccessful

The procedure for this is similar to the procedure for the WIT API test. The same three cases apply:

- 1. The output is correct and is to become the new basis for comparison.
- 2. The output is correct but too variable to become the new basis for comparison.
- 3. The output is incorrect.

Please note the following WIT-J-specific information:

• The test scripts are located in the following directory:

```
$WIT HOME/witj/test/scripts
```

• The test output is located in the following directory:

```
$WIT HOME/witj/test/data
```

- The diff files to examine are:
  - main-diff.output
  - error-diff.output
  - thread-diff.output
- The new output files are:
  - main-new.output
  - o error-new.output
  - thread-new.output
- The saved files for comparison are:
  - o main-saved.output
  - o error-saved.output
  - thread-saved.output

## 16. How to Access Old Versions of the Code

If you need access to an old version of the source code (WIT, MCL, etc.), the method to use depends on the date of the code that you want to retrieve. On 10/12/2011, we migrated the WIT-Projects source code from CVS on GSA to RTC on CS/next.

If you're looking for code more recent than 10/12/2011, you just use RTC: The procedure for this is given in [RTC Intro].

If you're looking for code earlier than 10/12/2011, you need to use CVS on GSA. When we migrated to RTC, we left the CVS repository intact, frozen in its state as of that date. So it contains the history of the code, going back to Feb. 2000, when we migrated to that CVS repository. To access our CVS repository on GSA (from Linux), you need to do the following:

- Be logged into GSA.
- export CVSROOT=/gsa/yktgsa/projects/w/wit/devbase
- Do a cvs checkout with the -D option to get code at the desired date.

# 17. How to Update the WIT Guide

The WIT Guide is written in FrameMaker, which runs on AIX and is installed on the MC4U (a.k.a. Agora) environment. The files for the WIT Guide are under a GSA directory, accessible from MC4U as:

```
/gsa/yktgsa/projects/w/wit/doc/wit-guide/
```

The WIT Guide is stored in several different files, one for each part of the Guide. The extension for FrameMaker files is .doc.. For example, wit2.doc is Chapter 2 and witTOC.doc is the Table of Contents. The top-level file that puts it all together is wit.book.

To make revisions to the WIT Guide, perform the following steps:

- If you haven't already done so, get an MC4U account.
- If you haven't already done so, find an MC4U machine that you can use. I have been using Anshul Gupta's MC4U machine dci1. So basically, all you have to do is ask Anshul if it's OK to use dci1 for this purpose. You won't be using disc space on the machine, that's on GSA; you'll be using CPU and memory.
- Remotely log into the MC4U machine from a Linux machine using ssh. This is how I do it:

```
ssh -Y wittrock@dci1
```

- In the above command, wittrock is my MC4U ID.
- When prompted, enter your MC4U password.
- This logs you into the machine, sending any X-Windows output to your screen. You need that, because FrameMaker uses X-Windows.
- Next, CD to the wit-guide directory:

```
cd /gsa/yktgsa/projects/w/wit/doc/wit-guide/
```

• Then issue the following:

```
/opt/IBM/mc4u/tools/bin/maker -file wit.book
```

- Wait awhile (40 seconds total when I tried).
- This first brings up a temporary splash window.
- It then brings up two small windows:
  - The Main Window, short and wide, with 5 buttons. The right-most button is "EXIT".
  - The Book Window, taller than wide. This shows wit.book and all the individual section files under it, such as witTOC.doc and wit2.doc.
- To work on, e.g., chapter 2, double click on wit2.doc.
- This brings up a full size window showing a page (or so) of Chapter 2.
- Refer to the FrameMaker manual (which I'm leaving with Dan) to figure it out from there.

At some point, after you've made changes to the Guide, you should do an "Update". This updates the TOC, the index, the cross-reference, etc. Here is the procedure:

- Go to the Book Window.
- Click "Edit".
- Click "Update Book...".
- This brings up a window with settings. You can leave them as they are or modify if you want want.
- Click "Update".
- It does the update. This takes a few seconds.

As you know, the WIT Guide is normally distributed as a PDF file. Any time you revise the guide, you should regenerate the PDF file. Here is the procedure:

- First do an Update, as above.
- Then go to the Book Window.
- · Click "File".
- Click "Print Book..."
- For "Destination", select "Single PDF File". (It's probably already selected.)
- In the text box, be sure it has the desired path name for the output PDF file, which should be wit.pdf under the wit-guide directory. I think what it has there is the fully resolved pathname (i.e., with all the GSA soft links resolved), so if that's what it seems to be, you can try that.
- Click "Print".
  - The window displays messages for a few seconds and then appears to be finished.
  - The actual creation of the wit.pdf file takes more like 30 seconds, but most of that is not accompanied by any indication in the window.

## 18.A Walk Through the Makefiles

One aspect of maintaining MCL, WIT, and WIT-J is the maintenance of their makefiles. The makefiles for WIT, etc. can be hard to follow, because in each case, the build process in question is defined not by just one makefile, but by several makefiles, nested together using include statements. To aid you in finding your way through these nested makefiles, this section will present a walk-through of one case of the WIT build process.

Suppose you are on the Linux platform and wish to build the WIT Stand-Alone Executable in debug mode. As explained in Section 6, you would set up some environment variables, cd to the <code>\$WIT\_HOME/wit/linux</code> directory, and then issue the following command:

```
make exe type=debug all
```

#### What happens?

#### Assumptions:

- WIT CPLEX HOME is defined as non-null, so CPLEX is to be embedded.
- WIT GEN PARSER=YES, so the parser is to be generated.
- MCL is built.
- Nothing in WIT has already been built.

The first thing that the make facility does is to read in all the relevant makefiles. The complete set of nested makefiles that are processed in response to the above command are as follows:

- \$WIT HOME/wit/linux/Makefile
  - This is the default makefile used by the make facility, i.e., Makefile on the current directory.
  - This makefile is responsible for the aspects of the build that are specific to both WIT and the Linux platform.
- \$WIT HOME/config/p linux.mk
  - This makefile is responsible for the aspects of the build that are specific to the Linux platform, but are independent of the program being built (WIT, SCE, etc.).
- \$WIT HOME/wit/src/appl.mk
  - This makefile is responsible for the aspects of the build that are specific to WIT, but are platform-independent.
- \$WIT HOME/config/ds.mk
  - This makefile is responsible for the aspects of the build that are (mostly) independent of both the program being built and the platform. (Not all aspects are used in all cases.)
- \$WIT HOME/config/t debug.mk
  - This makefile defines a few macros in a way that's specific to exe type=debug.
- \$WIT HOME/config/sfDefine.mk
- \$WIT\_HOME/config/legacy.mk

These two makefiles define a few macros that are not used by the makefiles for WIT, MCL, or WIT-J,

but are used for other programs in the WIT-Projects stream.

- \$WIT HOME/wit/src/sources.mk
  - This makefile defines the macro lib\_objects, which lists most of the object files that go into the WIT library.
- \$WIT HOME/wit/src/appl unix.mk
  - This makefile is responsible for the aspects of the build that are specific to WIT and apply to all Unix-like platforms, i.e., all of our platforms except Windows SDK.
  - o On Windows SDK, the makefile content that's functionally equivalent to wit/src/appl\_unix.mk is contained in wit/winsdk/Makefile.

The actual nesting of included makefiles can be represented as follows, where indentation indicates file inclusion:

- Makefile
  - o p\_linux.mk
  - o appl.mk
    - ds.mk
      - t debug.mk
      - sfDefine.mk
      - · legacy.mk
    - sources.mk
  - ∘ appl unix.mk

After the make facility has read in all the nested makefiles, it processes the rules in them. (Actually, it might be concurrent; I'm not sure.) As you know, the processing is hierarchical, starting with the requested target and working downward through a tree of out-of-date prerequisite targets, processing each prerequisite target before its dependent target. The following is a representation of the tree of targets for building the WIT Stand-Alone Executable when nothing is already built, with indentation indicating the prerequisite relationships:

<u>all</u>: The primary target is the all target, whose rule is specified in appl.mk. This rule takes no action of its own, but its prerequisite is wit:

- <u>wit</u>: The rule for this target is specified in appl\_unix.mk. It builds wit as an executable linked together from wit.o, and libwit.a, which are its prerequisites:
  - wit.o: This target is covered by the implicit rule for .o files, which compiles wit.o from wit.C. Actually, our makefiles don't specify this rule on linux; the make facility defines it based on macros that we define, e.g., CXX=/usr/bin/q++ in p linux.mk.
  - o <u>libwit.a</u>: The rule for this target is specified in appl\_unix.mk. It builds libwit.a as a static library formed from the .o files in lib\_objects, MclModule, CplexModule, and BuildDate.o, which are its prerequisites:
    - The .o files listed in lib\_objects: Most of these are covered by the implicit rule for .o files, which compiles them from the corresponding .C files. Two of the .o files, witParse.o and witLexer.o, have prerequisites: witParse.C and witLexer.C:
      - witParse.C: The rule for this target is specified in Makefile. It builds witParse.C from witParse.y, which is half of parser generation.
      - witLexer.C: The rule for this target is specified in Makefile. It builds witLexer.C from witLexer.l, which is the other half of parser generation.
    - <u>Session.o</u>: This .o file is listed in lib\_objects, but uses an explicit rule, specified in appl.mk, which compiles Session.o from Session.C with special flags.
    - MclModule: The rule for this target is specified in appl\_unix.mk. It builds MclModule as a pre-linked object file formed from the WIT object files that invoke MCL and the MCL library itself. Its prerequisites are the WIT object files that invoke MCL:
      - The WIT object files that invoke MCL: These are covered by the implicit rule for .o files.
    - <u>CplexModule</u>: The rule for this target is specified in appl\_unix.mk. It builds CplexModule as a pre-linked object file formed from CplexMgr.o and the CPLEX library. Its prerequisite is CplexMgr.o:
      - © <u>CplexMgr.o</u>: The rule for this target is specified in appl.mk. It compiles CplexMgr.o from CplexMgr.C with special flags.
    - **BuildDate.o**: The rule for this target is specified in appl\_unix.mk. The BuildDate.o target depends on all other aspects of WIT, but is compiled like any other .o file. Its purpose is to note the date on which WIT was built and store it as a string that can be used by WIT.

## 19. Conventions of the WIT Source Code

Before we look at the specifics of the WIT source code, it will be helpful to note some of its conventions:

- Class names begin with "Wit", e.g. "WitPart".
- Any time a class is mentioned in a context that does not require the actual class name, the "Wit" prefix is dropped:
  - In comments, class WitPart is called Part.
  - A local variable of type WitPart \*, might be called thePart.
  - A data member of type WitPart \*, might be called myPart .
  - The only exception to this is class WitRun, which is always called WitRun.
- Most classes are designed to have their instances accessed by pointers:
  - A typical local variable for a Part would be declared as "WitPart \* thePart;", not "WitPart thePart;".
- A few classes are designed to have their instances accessed without pointers. These more mostly utility/collection classes, such as FlexVec <Elem>.
- Most classes do not support const, because in normal usage, const instances are not expected to arise.
  - o Once again, the main exceptions to this are the collection classes; they usually do support const.
- The names of data members end with underscore, e.g., myPart\_.
- WIT uses quite a few macros.
- Most of the time, a class will be declared in a header file whose name matches the class name, without the "Wit" prefix, e.g., Part.h.
  - Sometimes several very small class declarations are placed in a single header file.
- Some of the time, a class will be implemented (defined) in a .C file whose name matches the class name, without the "Wit" prefix, e.g., Part.C.
  - Often several small class implementations are placed in a single .C file.
  - The purpose of putting more than one implementation in the same .C file is to reduce the number of compilation units, to get faster compiles.
- When the implementation of a class is in a .C file whose name does not match the name of the header file containing its declaration, the main comment for the class declaration will give the name of the implementation file. For example, the main comment for the declaration of class OptVar contains:

```
// Implemented in OptMisc.C.
```

# **20.Structural Concepts**

Before going any further, it will be helpful to define a few structural concepts that are relevant to WIT.

The WIT code consists primarily of many classes (hundreds). Most of WIT's classes are organized as subsystems. As defined in [patterns], a subsystem is "an independent group of classes that collaborate to fulfill a set of responsibilities". A subsystem may contain one or more other subsystems that fulfill narrower sets of responsibilities, thus creating layers. WIT's subsystems tend to be layered.

An important concept in WIT's structure is "ownership". Object the will be considered to own object the and only if the A has responsibility for:

- Maintaining a reference to theB
- Destroying theB

In most cases, the owning object will also have responsibility for creating the owned object.

A related concept is "holding". Object the A will be considered to hold object the C, if and only if:

- theA is theC, or
- There is an object theB, such that:
  - theA owns theB, and
  - theB holds theC

(Note that this is a recursive definition.) "Hold" is the transitive and reflexive closure of "own": An object holds itself and all the objects that it owns and all the objects that they own and so on.

Class C is called the "holder" of subsystem S, if and only if:

- there is at most one an instance of C in a WitRun, and
- that instance holds all the objects in the WitRun that are instances of classes in S.

Many of WIT's subsystems employ the Facade pattern. The definitive explanation of the Facade pattern is given in [Patterns], but it can be summarized as follows: You have a subsystem, and one of its classes, the facade class, functions as the single point of contact (or main point of contact) to the rest of the subsystem from objects outside the subsystem. When an object outside the subsystem needs to use the functionality of the subsystem, it normally invokes a member function of the facade class, which relays the request to other classes of the subsystem (internal classes). The basic purpose of using facades is to decouple the subsystems, to make each subsystem appear as simple as possible to the rest of the program. It's a kind of encapsulation at the subsystem level.

Actually, as defined in [Patterns], the facade class doesn't have to be a strict gate keeper of the subsystem; outside objects are allowed to access the internal classes directly, if necessary. In contrast, most of WIT's facades are "strict" facades: access to the internal objects from outside objects is impossible, because the pointers to the internal objects are not made available outside the subsystem. This creates strong subsystem encapsulation.

In WIT, a facade of a subsystem is always (I think) the holder of that subsystem, but a holder of a subsystem doesn't necessarily need to be a facade for it.

# 21.A Structural Overview of WIT

The section will present an overview of the structure of WIT. The approach will be to discuss the holder classes of the main subsystems of WIT, along with other related classes, starting from the outside and working in.

#### WitRun:

- A WIT application program will own one or more WitRuns.
- As you know, most of the API functions take a Witrun pointer as the first argument. These functions are sometimes called the "outer API functions". For almost every outer API function, there is a corresponding public non-static member function of class Witrun with the same (or very similar) name. These are called the "inner API functions". The inner API function will have an argument list similar to the outer one, but without the Witrun argument. In almost all cases, the outer API function calls the matching inner one, invoking it on the Witrun and passing the other arguments.
- An inner API function has responsibility for:
  - Error checking
  - Issuing relevant messages
  - Translating the arguments into terms suitable for internal WIT functions (and the reverse)
  - Calling the appropriate internal WIT function(s)
- Because it implements almost the entire API, class WitRun is very large. For this reason, while its declaration is entirely in WitRun.h, its implementation is spread out across several files, each responsible for a different aspect of the API: WitRun.C, globApi.C, optApi.C, stochApi.C, partApi.C, demApi.C, opnApi.C, bomApi.C, subApi.C, bopApi.C, and msgApi.C.
- Clearly, WitRun is the holder and strict facade for the whole of WIT.
- More specifically, WitRun is the holder of the API subsystem, which implements the API.

#### ApiMgr:

- A WitRun owns one ApiMgr., part of the API subsystem.
- Responsible for maintaining the state of API, particularly when entering or leaving an API function. Also handles exceptions thrown from within WIT.

#### Session:

- A WitRun owns one Session.
- This is the holder of the Session Subsystem, which is responsible for all non-API aspects of WIT...

# MsgFacility:

- A Session owns one MsgFacility.
- This is the holder of the Message Subsystem, which is responsible for handling WITs messages. The classes of the message facility are the only classes that make direct calls to MCL. MsgFacility is a non-strict facade for the Message Subsystem.

#### Problem:

- A Session owns 0 or 1 Problems: 0 at first; 1 after witInitialize is called.
- This is the holder of the Problem Subsystem, which is responsible for all non-API aspects of WIT that only apply after witInitialize has been called.
- The Problem subsystem is the "main aspect" of WIT, once you get past the outer layers.
- A Problem is the all-important central object of a WitRun: It has direct ownership of many important holder objects, and many objects in the Problem Subsystem have a pointer back to the Problem that holds them. It connects the internal objects of WIT together.

### CompMgr:

- A Problem owns one CompMgr.
- This is the holder of the Component Subsystem, which is responsible for the Components of a WitRun. (See below for the definition of a Component.)
- A CompMgr owns all of the Components for a WitRun: It provides multiple forms of access to them and is responsible for deleting them for witDeleteRun and witPurgeData.

#### Component:

- Class Component is the base case for the Component classes of WIT, the classes whose instances represent parts, operations. etc., the "WIT Data Objects".
- The following shows the inheritance hierarchy under class Component, where "class A inherits from class B" is indicated by B being indented under A:
- o Component

GlobalComp
 Maintains global data not for opt implosion

OptComp
 Maintains global data for opt implosion

DelComp
 Deletable Component (i.e., subject to witPurgeData)

Node in the BOM graph

o Part

Material Material PartCapacity Capacity Part

o Operation

BillEntry

Consentry Consumption Bill Entry

BomEntry BOM EntrySubEntry SubstituteBopEntry BOP Entry

• Demand

• A CompMgr owns one GlobalComp and and OptComp.

- A Problem owns one instance of each of the following subsystem holder classes:
  - o Preprocessor:
    - Holder and facade for the Preprocessing Subsystem, which is responsible for preprocessing.
  - o Postprocessor:
    - Holder and facade for the Postprocessing Subsystem, which is responsible for ... well, you get the idea.
  - HeurImploder:
    - Holder and facade for the Heuristic Implosion Subsystem.
  - o EqAllocator:
    - Holder and facade for the Equitable Allocation Subsystem.
  - o HeurAllMgr:
    - Holder and facade for the Heuristic Allocation Subsystem.
  - o DetImploder:
    - Holder and facade for the Deterministic Optimizing Implosion Subsystem.
  - StochImploder:
    - Holder and facade for the Stochastic Implosion Subsystem.
  - PipMgr:
    - Holder and facade for the PIP Subsystem.
  - o OrigMrpExp:
    - Holder and facade for the MRP Subsystem.
  - FSS
    - Holder and facade for the FSS Subsystem.
  - o DataReader:
    - Holder and facade for the Data Reading Subsystem, which is responsible for reading an input data file.
  - ∘ DataWriter:
    - Holder and facade for the Data Writing Subsystem, which is responsible for writing an input data file.
  - ∘ SolnWriter:
    - Holder and facade for the Solution Writing Subsystem, which is responsible for writing an solution files.

The following shows the high-level classes of WIT, where ownership is represented by indentation:

- WitRun
  - ApiMgr
  - Session
    - MsgFacility
    - Problem
      - CompMgr
        - Component
      - Preprocesser
      - Postprocessor:
      - HeurImploder:
      - EqAllocator:
      - HeurAllMgr:
      - DetImploder:
      - StochImploder:
      - PipMgr:
      - OrigMrpExp:
      - FSS:
      - DataReader:
      - DataWriter:
      - SolnWriter

Note: The Data Reading Subsystem was mostly written by Juan Lafuente. The documentation for his code is in two files located on GSA at:

```
{yktgsa}/projects/w/wit/doc/data-reader/witDoc.txt
{yktgsa}/projects/w/wit/doc/data-reader/witSyntx.txt
```

The code has evolved somewhat since Juan wrote these documents, but their content is still relevant.

# 22. How to Add a Message to WIT

As you know, WIT produces its output by issuing "messages", which can be controlled in various ways by the application program. If you are making modifications to WIT, there's a good chance that you will need to add/modify/remove one or more of WIT's messages. This section will explain how to add a new message to WIT. (How to modify or remove a message should be easy enough to figure out.)

WIT works with messages by invoking MCL. A message is an object, an instance of the WIT class WitMsg, which inherits from the MCL class MclMsg. Adding a new message to WIT's output, normally consists of the following three steps:

- 1. Add code to create the message.
- 2. Add code to issue the message,
- 3. Add code to test the message, if possible.

To create a new message, you add code to the implementation of class MsgBuilder (in MsgBuilder.C). Here is an example:

```
makeMsg (
   "demandIdDdMsg",
   134,
   info_,
   "Part \"%1$s\",\n"
   "Demand Stream \"%2$s\":");

currentMsg ->preceedingLineFeeds (1);
```

This code is located in the buildMsgs function of class MsgBuilder.

The main code to be added is call to makeMsg, which is a member function of class MsgBuilder. The arguments to makeMsg are as follows:

- theMsqID ("demandIdDdMsq"):
  - This argument is of type MsgID, which is just a typedef for const char \*. This will be the message's message ID, the string that uniquely identifies it internally among WIT's messages.
- theExtNum (134):
  - This argument (of type int) will be the message's external number, the number that uniquely identifies it externally among WIT's messages. By default, this number is printed when the message is issued, e.g., "WIT0134I". It is used as an argument to various API functions that manage the messages. Note that the messages must be created in order of increasing external number. If this condition is violated, witNewRun will print an error statement to stderr and terminate.
- theLevel(info):
  - This argument (of type Mcllevel) will be the message's message level. This concept is explained in [WIT Guide]. It can take any of these four values, defined as data members of class MsgBuilder:
    - info
    - warning
    - severe\_
    - fatal

- textVal ("Part \"%1\$s\",\n" "Demand Stream \"%2\$s\":"):
  - This argument (of type const char \*) will be the message's text string. This will be explained below

By convention, the last characters of the message ID correspond to the message level as follows:

Informational: "Msg"
Warning: "Wmsg"
Severe: "Smsg"
Fatal: "Fmsg"

After the message is created with makeMsg, its attributes can be set by calling member functions on it. To make this convenient, there is a data member, MsgBuilder::currentMsg\_(of type Msg \*), whose value is the most recently created message. In the example, the following line sets an attribute of the message that was just created:

```
currentMsg ->preceedingLineFeeds (1);
```

This causes one linefeed to be added to the beginning of the output of the message. In general, some of the message attributes belong to class MclMsg and some belong to class WitMsg. For more information, see the declarations of these two classes.

The main task of creating a message is to define its text string. The text string of a message works similarly to the format string of a printf statement, but with the following differences:

- The arguments to the text string are explicitly numbered. In the example above %2\$s indicates that the second argument is to be inserted at that point in the text and it must be a string argument.
  - The original purpose of explicitly numbering the arguments was to allow the message texts to be translated into other languages, which use different word orderings, but it's pretty clear by now that that is unlikely to happen.
- The set of valid format flags is different than the flags for a printf statement. These are the valid format flags for MCL and WIT:
  - b: The argument must be of type bool or int or size t or long and is displayed as a boolean.
  - **d**: The argument must be of type int or size tor long.
  - **f**: The argument must be of type double.
  - **g**: The argument must be of type double.
  - s: The argument must be of type const char \* or WitString or WitMsgFrag.
  - $\circ$  m: The argument must be of type <code>WitMsgFrag</code>. See below for an explanation of class <code>WitMsgFrag</code>.
- There is an option to specify a vector type argument, by putting a "v" after the argument number, for example:
  - " External supply volumes:%1v\$8.0f"
- When "v" is specified, the argument must be a WitVector type, for example, WitVector <double>, if the "f" format is specified, as above.

- The full specification of an argument consists of:
  - %, followed by
  - the argument number, followed by
  - o an optional v for vector, followed by
  - \$, followed by
  - o an optional field width, followed by
  - o an optional precision, followed by
  - the format flag

After you have added the code to create a message, you need to add code to issue it. Here is an example of how to issue a message:

```
myMsgFac () ("demandIdDdMsg",
    demandedPartName (),
    demandName );
```

This code is in Demand. C. The message identifies a Demand for witDisplayData.

Here are the steps to take for issuing a message.

- First, you specify a reference to the MsgFacility for the Session in which your code is operating:
  - In most cases you will be in the implementation of some class that inherits from class ProbAssoc. If so, you just invoke the myMsgFac () function of class ProbAssoc and it returns a reference to the MsgFacility. That is what's being done in the example.
  - Some classes that do not inherit from class ProbAssoc have their own version of myMsgFac (), so you can just use that version. (for example WitRun and ApiMgr)
  - Otherwise, you need to call myMsqFac () on some instance of a class that has it.
- Next, you invoke the overloaded function call operator, "()", on the MsgFacility. This is the MsgFacility's message issuing function:
  - $\circ$  The first argument to this function is the message ID of the message to be issued, e.g., "demandIdDdMsg".
  - $\circ$  The subsequent arguments to this function are the arguments to the message, e.g., demandedPartName () and demandName\_.
    - The message issuing function will accept up to 15 message arguments.

After you have added the code to issue a message, you may need to add a test for it to the testing procedure:

- In some cases, you're adding a message to code that's already being invoked by an existing test. In this case, the output of the message will show up in the "diff" output when you do that test. All you need to do then is to check that the output is as desired and then perform the appropriate output saving procedure as explained in section 8.
- Otherwise, if the output of the new message doesn't show up in the "diff" output of any test, you should modify the tests so that it shows up somewhere.

- If it's an error message that can be triggered from the Stand-Alone Executable, you should revise the Stand-Alone Test, adding a new case that causes that error condition. See section 14.
- If it's an error message that cannot be triggered from the Stand-Alone Executable, you should revise the error test portion of the API Test, adding a new case that causes that error condition. See section 9.
- If it's not an error message (i.e., the message level is "informational" or "warning"), you should add code to msqAll that issues the message, if this is practical.
- If you have added a non-error message that is not issued from msgAll, msgAll will issue an message identifying your message as a "testable" message that it did not issue. If it's not feasible to have msgAll issue the new message (e.g. it only issues from the Stand-Alone Executable), you should turn off the "testable" attribute of the new message, by adding the following code just after the message was created with makeMsg:

```
currentMsg ->testable (false);
```

This will keep msgAll from listing it as an unissued testable message. In this case, you should add it to the Stand-Alone Test, if possible.

#### Class WitMsqFraq

A MsgFrag (i.e. "message fragment") is an object that stores a string (its "text") and is intended to be used as a argument to a message. When a message is issued with a MsgFrag argument, the text of the MsgFrag is inserted into the output. The original purpose of using MsgFrags as arguments instead of strings was to allow the text to be translated into other languages. But once again, this now seems unlikely to happen. Nevertheless, since the code has quite a few MsgFrags, you may have to deal with them at some point.

A MsgFrag has a MsgFrag ID, which is a string that uniquely identifies it internally among WIT's MsgFrags. WIT's MsgFrags are created in the buildMsgFrags function of class MsgBuilder. The process is simpler than building a message and so further explanation will be given here.

To get an existing MsgFrag you invoke the myFrag function of class MsgFacility. This function takes one argument: the MsgFrag ID and returns the corresponding MsgFrag. You get the MsgFacility reference in the same way as you do for calling the message issuing function.

Here is an example of code that issues a message that uses a MsgFrag as an argument:

```
myMsgFac () ("categorySizeDdMsg",
    myMsgFac ().myFrag ("capacityFrag"),
    nCapacities);
```

This code is located in Problem.C. The text for the capacityFrag MsgFrag is "Capacity", which is inserted into the output of the message.

# 23. How to Add an Attribute to WIT

When you add a new capability to WIT, usually, you'll need to add one or more attributes to control the new capability, or get new data in or out, etc. The procedure for adding a new attribute is well-defined and depends on whether or not the attribute is modifiable (i.e., its value can be explicitly set from the application program). The procedure given below will use the following hypothetical attribute as an example:

Attribute: exampleVol
 Type: Vector of floats
 Owning Component Class: Operation
 Modifiable? Yes

To add a new attribute to WIT, perform the following steps:

- If the attribute is modifiable, add its default value function to the declaration of the owning class:
  - For example, in Operation,h:

```
defaultValue (double defExampleVol, 0.0)
```

- This is a static function member of the owning class.
- Normally you use the defaultValue macro, as in the example. This creates the declaration of an inline default value function, so no further implementation is needed.
- For a vector valued attribute, you usually just specify the default value as a scalar, as in the example.
- Note that any type that is externally a float type is stored internally as the corresponding double type, as in the example.
- The default value functions are declared in the same order as the data members for the attributes.
- Add the data member for the attribute to the declaration of the owning class:
  - For example, in Operation.h:

```
WitDblFlexVec exampleVol;
```

- The name of the data member is the name of the attribute with an underscore suffix.
- o In the example, DblflexVec is used as the type. This a space-efficient class for storing a time-vector of doubles: If the value is the same in all periods, it tends to store the vector as a scalar. It's the usual internal type of a "float vector" attribute. See FlexVec.h.
- A comment explaining the attribute is placed under its data member declaration.
- The attribute data members are declared in an order that seems "logical": Input attributes are placed together. Opt implosion attributes are placed together, etc.

- Add the initializer for the attribute data member to the constructor of the owning class:
  - For example, in Operation.C:

```
exampleVol (myProblem (), defExampleVol ()),
```

- If the attribute is modifiable, you invoke the default value function for this; otherwise, just you just hard code the value.
- The initializers go in the same order as the declarations.
- Add the access function for the attribute to the declaration of the owning class:
  - For example, in Operation,h:

```
accessFunc (const WitDblFlexVec &, exampleVol)
```

- This is a public member function that returns the value of the attribute.
- Normally you use the accessFunc macro, as in the example. This creates the declaration of an inline access function, so no further implementation is needed. The name of the access function is the same as the name of the attribute.
- Note that in the example, the returned value has a const reference type. This reflects the fact that class DblFlexVec deliberately avoids having a copy constructor, so as to prevent needless expensive copying.
- The access functions are declared in the same order as the data members for the attributes.
- Add displaying code for the attribute to the display member function of the owning class:
  - For example, in Operation::display:

```
myProblem ()->display ("exampleVolDdMsg", exampleVol);
```

- The display function of a Component class is the function that displays the value of the Component's attributes for witDisplayData.
- This is done in a variety of ways; see the display functions for examples.
- This will normally involve either adding a new message (as in the example) or modifying an existing one. See section 22, "How to Add a Message to WIT".

- If the attribute is modifiable, add copying code for it to the copyAttrsFrom member function of the owning class:
  - For example, in Operation::copyAttrsFrom:

```
exampleVol = theOpn->exampleVol;
```

- The copyAttrsFrom function of a Component class is the function that copies the value of each modifiable attribute from another instance of the Component class into the current instance. It is used by witCopyData and, e.g., witCopyOperationData.
- The copying code is normally placed in the same order as the data members for the attributes.
- If the attribute is modifiable, add its "set" function to the owning class:
  - For example, in Operation.h:

```
void setExampleVol (const WitIVRealArg &);
```

- The "set" function has the following responsibilities:
  - Final validity checking of the argument value, via asserts.
    - Note that primary validity checking (via severe error messages) is the responsibility of the API, not this function.
  - Revising the state of the WitRun; for example, taking it out of the "preprocessed" state, if appropriate.
  - Setting the value of the data member to the argument value.
- Note that in the example, the argument is of type const IVRealArg &. This is a type that is used by the inner API and will be explained later in this section.
- The "set" functions are placed in the same order as the data members for the attributes.
- If the attribute is not modifiable, some other means of giving it a value from within WIT will need to be implemented.
  - This is done is a variety of ways, beyond the "rudimentary" scope of this document.
- If the attribute requires special treatment in stochastic mode, consider adding it to StochAttMgr::makeStochAtts.
  - This is rare.

- Add the inner API "get" function for the attribute:
  - For example, in WitRun.h:

```
void witGetOperationExampleVol (
   const char * operationName,
   const WitOVRealArg & exampleVol);
```

- The inner API "get" functions are declared in WitRun.h.
- They are implemented in the Component-class-specific inner API source files, e.g. optApi.C.
- The inner API "get" function has responsibility for:
  - Validity checking of the arguments, issuing severe error messages, as needed.
  - Issuing the relevant informational message(s).
  - Retrieving the requested value from the Component.
  - Setting the argument to the retrieved value.
- In the example, the argument is of type const OVRealArg &. The name of this class means "Output Vector Real Argument". It represents vector of real numbers for output. In the outer API, this corresponds to an argument of type float \* \* or of type double \* \*. When interacting with WIT internally, it acts like a vector of doubles. This is one of the classes that enables WIT to have two versions of its real valued API functions, one for floats and one for doubles.
- The inner API "get" functions are ordered alphabetically.

- If the attribute is modifiable, add the inner API "set" function for the attribute:
  - For example, in WitRun.h:

```
void witSetOperationExampleVol (
   const char * operationName,
   const WitIVRealArg & exampleVol);
```

- The inner API "set" functions are declared in WitRun.h.
- They are implemented in the Component-class-specific inner API source files, e.g. optApi.C.
- The inner API "set" function has responsibility for:
  - Validity checking of the arguments, issuing severe error messages, as needed.
  - Issuing the relevant informational message(s).
  - Calling the Component's "set" method.
- o In the example, the argument is of type const IVRealArg &. The name of this class means "Input Vector Real Argument". It represents vector of real numbers for input. In the outer API, this corresponds to an argument of type const float \* or of type const double \*. When interacting with WIT internally, it acts like a vector of doubles. This is one of the classes that enables WIT to have two versions of its real valued API functions, one for floats and one for doubles.
- The inner API "set" functions are ordered alphabetically.

- Add the outer API "get" function for the attribute:
  - For example, in wit.h:

- The following comments apply to all outer API functions, not just "get" functions for attributes:
  - The outer API functions are declared in wit.h and implemented in api.C.
  - An outer API function has responsibility for:
    - Calling member functions of class ApiMgr, to maintain the state of the API.
    - Calling the corresponding inner API function on the WitRun that's the first argument of the outer API function and passing the other arguments.
    - Doing all this in the context of a try block that will catch any exception thrown from within WIT. In particular, when WIT issues a severe or fatal error message (anywhere inside of WIT), it throws an exception that is to be caught by the outer API function's try block.
    - If an exception is caught, passing it to the ApiMgr for processing.
  - Since the above responsibilities are very uniform and must be fulfilled by hundreds of API functions, they are encoded into a macro: STANDARD\_API\_IMPL. Most outer API functions call this macro.
  - For example, in api.C:

• The outer API functions are ordered alphabetically.

- If the type of the attribute is a float/double type (as in the example), you actually need to add two versions of the output "get" function:
  - One version will use the float type. This version will have the ordinary name of the API function. The example above shows that case.
  - The other version will use the double type. This version will have the name with "Dbl" appended to the end, for example:

- The implementation of an outer API function that has double arguments uses a different macro to call the inner API function: STANDARD\_DBL\_API\_IMPL .
- Both the float and the double outer API function call the same inner API function, which converts their float/double arguments into the appropriate "RealArg" arguments.
- If the attribute is modifiable, add the outer API "set" function for the attribute:
  - For example, in wit.h:

The comments for the outer API "get" functions pretty much apply here, too (i.e., calling the macro, float vs. double, etc.).

- If the attribute is modifiable, add it to the Data Reading Subsystem:
  - For example, in SymTable.h:

```
static WitParseRC witSetOperationExampleVol();
```

• And in SymTable.C:

```
{"set_operation_exampleVol", 1,
WitSymTable::witSetOperationExampleVo 1,
{WitDRParmType::doubleVector}},
```

• Also in SymTable.C:

```
WitParseRC WitSymTable::witSetOperationExampleVol()
{
    ...
}
```

- This is the code that allows witReadData to read the attribute.
- It's Juan Lafuente's code; I don't really know how it works.
- Basically, you copy an existing case and modify it to your case.
- All of this code is organized alphabetically.

- If the attribute is modifiable, add writing code for it to the writeDataAttrs member function of the owning class:
  - For example, in Operation::writeDataAttrs:

```
myDataWriter ()->writeVector (
    "exampleVol",
    exampleVol_,
    defExampleVol ());
```

- The writeDataAttrs function of a Component class is the function that writes the value of each modifiable attribute to the message file for witWriteData.
- The writing code is normally placed in the same order as the data members for the attributes.
- Add the following test code to wit/api-test/apiAll.c:
  - If the attribute is modifiable, add a call to the API "set" function for it.
  - If the attribute is modifiable and is of a float/double type, add a call to the double variant of the API "set" function for it.
  - Add a call to the API "get" function for it.
  - If the attribute is of a float/double type, add a call to the double variant of the API "get" function for it.
- Document the attribute in the WIT Guide:
  - Add an entry to Chapter 2, explaining the attribute.
  - If the attribute is modifiable, add a row for it to Table 6 in Chapter 4.
  - Add an entry for the API "get" function for it to Chapter 5.
  - If the attribute is modifiable, add an entry for the API "set" function for it to Chapter 5.
  - The "double" variants of API functions are not listed exhaustively in Chapter 5.
  - These are all organized alphabetically.
  - Mention the attribute and its API functions in the "Change History' in the Preface.
- Add the attribute to WIT-J. See section 24.

# 24. How to Add an Attribute to WIT-J

If you add an attribute to WIT, you should also add it to WIT-J. Fortunately, the procedure for adding an attribute to WIT-J is much simpler than the procedure for adding one to WIT. Note that in WIT-J, attributes are actual objects. More specifically, for each WIT attribute, there is a C++ object for it in WIT-J and a Java object for it in WIT-J. Here are the steps to follow:

- Add code creating the C++ version of the attribute to AttBldr::buildAtts, which is implemented in AttBldr.C:
  - For example:

- For more information on which constructor to invoke and the meaning of its arguments, see the declarations in ScalarAtts.h and VectorAtts.h.
- Note that WIT-J uses only the double variant of a float/double attribute.
- Add code creating and declaring the Java version of the attribute to the public static fields of class Attribute in Attribute.java:
  - For example:

- For more information, see the newAtt methods of class Attribute. (There are a few of them.)
- Note that the Java name for an Attribute uses all upper case. This is explained in [WIT-J Guide].
- Add a display call for the Attribute to the displayAttributes method of class UnitTester in the WIT-J Test code:
  - For example:

```
display (EXAMPLE VOL);
```

• All of the above are organized alphabetically.

## 25. How to Add/Remove/Rename Source Files

As was indicated in the makefile walk-through (Section 18), one of the WIT makefiles defines a macro, lib\_objects, that lists most of the WIT object file names. Thus if you add or remove or rename a WIT .C source file, you'll need to update this list. (Nothing needs to be done for .h files.) Here are the procedures:

#### The macro is in:

```
$WIT_HOME/wit/src/sources.mk
```

### Adding a .C source file to WIT:

- Add its name to the lib\_objects macro, with a \$ (obj\_suffix) ending.
- Note that this list is kept in alphabetical order, to ease maintenance.
- Invoke make depend.

# Removing a source file from WIT:

- Remove its name from lib\_objects.
- Invoke both make depend and make clean.

# Renaming a source file from WIT:

- Change its name in lib objects.
- Move the name alphabetically.
- Invoke both make depend and make clean.

## For MCL:

The procedures are the name. The macro is in:

```
$WIT HOME/mcl/src/sources.mk
```

#### For WIT-J:

The procedures are the name. The macro is in:

```
$WIT HOME/witj/cpp/src/sources.mk
```

Note that the procedures apply only to the C++ portion of the code.

# 26. How to Update the Copyright Dates

Maintaining MCL/WIT/WIT-J entails updating their copyright dates, as appropriate. This section explains when and how that should be done (to the best of my understanding).

WIT's copyright notices are part of its "proprietary statements", which are required by the IBM Corporate Standard on Copyrights: [Corp Std]. I worked out the proprietary statements for WIT in 2011 as part of preparing the Certificate of Originality (COO) for WIT that was required for the global deployment of GIView. (See [COO].) Here are my interpretations of the IBM Corporate Standard on Copyrights as it pertains to the WIT software that's covered by the COO:

- The WIT software covered by the COO consists of those aspects of WIT that would be distributed outside of IBM as part of GIView, namely the WIT library. On Unix-like platforms this is libwit.a; on Windows, it's wit.lib.
- Therefore, the WIT software covered by the COO includes:
  - The WIT object code
  - The MCL object code
- The WIT software covered by the COO does not include:
  - The CPLEX library: This is "Preexisting IBM Material".
  - WIT/MCL source code.
  - WIT/MCL documentation.
  - o WIT-J.
- The WIT library is an "object module" in the sense of the Corporate Standard and not an "object code program". GIView/planner (or something above it) is the "program". See definition 5.13 of [Corp Std].

The Corporate Standard requires object modules to contain "proprietary statements" that follow certain formats. In accordance with this Standard, WIT contains two distinct kinds of proprietary statements:

- An object code proprietary statement
- A source code proprietary statement

### The Object Code Proprietary Statement

This (currently) is WIT's object code proprietary statement:

\_\_\_\_\_

Licensed Materials - Property of IBM

Watson Implosion Technology

(C) Copyright IBM Corp. 1993, 2012 All Rights Reserved

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

\_\_\_\_\_\_

The object code proprietary statement is stored as a string-valued static data member, proprietaryStmt\_, of class Session, which is initialized to that value in Session.C. This proprietary statement string is visible in three ways:

- It's visible in the library itself: If you bring up libwit.a in a text editor and search for that string, you'll find it. This was required by the Corporate Standard.
- It's in memory somewhere for any application program that uses WIT. I haven't verified this, but storing it as the value of a static data member should have that effect. This was required by the Corporate Standard.
- By default, it's printed at the beginning of the WIT message file. I don't think this is required by the Corporate Standard, but it seems to be in the spirit of it. It's WIT's equivalent of a title screen, which is required for a program, but presumably not required for a module.

To change the object code proprietary statement, simply change the initialization statement of Session::proprietaryStmt\_in Session.C.

# What to Update and When to

It's the second year in the copyright notice (currently 2012) that would need to be updated sometimes. As explained in [Corp Std], subsection 7.2, this is called "Year 2". As explained in [Corp Std], subsection 7.2.4.1, Year 2 is to be updated to the current year, whenever "the module has been changed substantially and released". You'll need to use your judgement to decide what's a substantial change. I would consider a change to WIT to be "released", if:

- It has been delivered to the RTC WIT-Projects stream.
- It is not restricted to "development mode".
  - See section 6 for how to make a partially implemented capability unavailable to production builds of WIT by restricting it to development mode.

In my opinion, the above two conditions are sufficient to constitute a release, because as soon as an unrestricted capability has been put into the WIT-Projects stream, the GIView team is free to incorporate the new capability into GIView/planner and deploy it externally, with no further involvement from the developer. Therefore, the Year 2 of the copyright notice should be updated to the current year whenever the following have occurred:

- A substantial change has been made to WIT.
- It is not restricted to development mode.
- It has been delivered to the RTC WIT-Projects stream.

### The Source Code Proprietary Statement

This (currently) is WIT's source code proprietary statement:

This statement is required in each "source module", i.e., each source file of WIT.

Year 2 of the source code proprietary statement should be updated under the same circumstances as Year 2 of the object code proprietary statement. Since this entails changing many files, I recommend using a script.

### **MCL**

MCL has its own proprietary statements, which follow the same rules as those for WIT. However, I think it's likely that no further substantial changes will ever be made to MCL and so its proprietary statements will probably never need to be changed. MCL's current Year 2 is 2005.

### References

[COO] Certificate of Originality, Certificate #YOR720110080, "Watson Implosion Technology" Available on the Certificates of Originality database on Lotus Notes

[Corp Std] "Proprietary Protection for IBM Materials (Including Copyright): Programs, Machine Code, and Supporting Documentation". IBM Corporate Standard C-S 0-6045-002, 1999-03.

Available at:

http://w3-03.ibm.com/ services/intellectual\_property/download/copyright\_std.pdf

[Patterns] E. Gamma, R. Helm, R. Johnson, J. Vlissides. Design Patterns: Elements of Reusable Object-Oriented Software. Addison-Wesley, Reading, MA, 1995. ISBN 0201633612.

[RTC Intro] R. Wittrock. 2012. "Getting Started with the WIT-Projects Stream in RTC on CS/Next". Available on GSA at:

{yktgsa}/projects/w/wit/doc/rtc/wit-rtc.pdf

[Win SDK] R. Wittrock. 2012. "The Windows SDK Platform for WIT Software Projects". Available on GSA at:

{yktgsa}/projects/w/wit/doc/winsdk/wit-winsdk.pdf

[WIT Guide] IBM. 2012. "Watson Implosion Technology, User's Guide and Reference" Release 8.0. Available on GSA at:

{yktgsa}/projects/w/wit/doc/wit-guide/wit.pdf

[WIT Intro] R. Wittrock. 2013. "An Introduction to WIT: Watson Implosion Technology" Second Edition. Available on GSA at:

{yktgsa}/projects/w/wit/doc/wit-intro-2/wit-intro-2.pdf

[WIT-J Guide] R. Wittrock. 2012. "WIT-J: Watson Implosion Technology – Java Interface, Application Developer's Guide". Available on GSA at:

{yktqsa}/projects/w/wit/doc/wit-j-quide/wit-j-quide.pdf

[WIT-J Set-Up] R. Wittrock. 2012. "How to Set Up WIT-J for Development". Available on RTC at:

{WIT-Projects Stream}/witj/doc/Set-Up-WIT-J.txt