

# PDMWorks API (.NET, legacy) — Reference (2/4): IPDMWDocument-IPDMWDocuments

SOLIDWORKS API Documentation (converted from CHM)

# IPDMWDocument (Type)

## IPDMWDocument Interface

[See Also](#) [Members](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocument Interface

Represents and provides access to a single file that is checked into the vault. Some document properties, such as configuration, references, and where used, only work with SOLIDWORKS documents (.sldprt, .sldasm, and .slddrw files).

**NOTE:** Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

### .NET Syntax

Visual Basic (Declaration)

Public Interface IPDMWDocument

Visual Basic (Usage)



Dim instance As [IPDMWDocument](#)

C#

public interface IPDMWDocument

C++/CLI

public interface class IPDMWDocument

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument](#).

### Example

- [Extract Embedded eDrawings Data \(VBA\)](#)
- [Get Specific Document \(VBA\)](#)
- [List Assemblies Where Part Used \(VBA\)](#)
- [Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

### Accessors

- [IPDMWConfiguration::Document](#)
- [IPDMWConnection::CheckIn](#)
- [IPDMWConnection::GetSpecificDocument](#)
- [IPDMWDocuments::Item](#)
- [IPDMWLink::Document](#)
- [IPDMWSearchResult::Document](#)

### See Also

- [IPDMWDocument Members](#)
- [PDMWorks.Interop.pdmworks Namespace](#)
- [IPDMWDocuments Interface](#)

## IPDMWDocument Interface Methods

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocument Interface

For a list of all members of this type, see [IPDMWDocument members](#).

### Public Methods

| Name                                                                                                                     | Description                                                                                                                                                      |
|--------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|  <a href="#">AddNote</a>                | Adds a note to the document.                                                                                                                                     |
|  <a href="#">BumpRevision</a>           | Changes the revision number of the document.                                                                                                                     |
|  <a href="#">ChangeOwner</a>            | Changes the document's owner.                                                                                                                                    |
|  <a href="#">ChangeProject</a>          | Moves the document to the specified project.                                                                                                                     |
|  <a href="#">ChangeStatus</a>           | Changes the lifecycle status of the document to the specified lifecycle status.                                                                                  |
|  <a href="#">GetDocumentSize</a>        | Gets the size (in bytes) of the document.                                                                                                                        |
|  <a href="#">GetEmbeddedEDWAsBase64</a> | Gets embedded eDrawing data with Base64 encoding, if available.                                                                                                  |
|  <a href="#">GetStatus</a>              | Gets the lifecycle status of the document.                                                                                                                       |
|  <a href="#">ReleaseOwnership</a>       | Allows you to release ownership of a document.                                                                                                                   |
|  <a href="#">Save</a>                   | Copies the document.                                                                                                                                             |
|  <a href="#">SaveAsPDF</a>              | Gets the PDF file for this drawing document from the vault, if the setting to create a PDF file of a drawing document in the vault during check-in was selected. |
|  <a href="#">SaveEmbeddedEDW</a>        | Saves the eDrawings embedded in the SOLIDWORKS document, if one exists.                                                                                          |
|  <a href="#">TakeOwnership</a>          | Allows you to take ownership of a document.                                                                                                                      |

[Top](#)

## See Also

[IPDMWDocument Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocuments Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

## IPDMWDocument Interface Members

[See Also](#) [Properties](#) [Methods](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocument Interface

The following tables list the members exposed by [IPDMWDocument](#).

## Public Properties

| Name                                                                                                               | Description                                                                                      |
|--------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------|
|  <a href="#">Attachments</a>    | Gets the non-SOLIDWORKS attachments for this SOLIDWORKS document.                                |
|  <a href="#">Configurations</a> | Gets the configurations available for the specified document and revision.                       |
|  <a href="#">DateModified</a>   | Gets the date and time that this document was last modified.                                     |
|  <a href="#">Description</a>    | Gets the description of the document.                                                            |
|  <a href="#">ExtReferences</a>  | Gets the links to external documents that this document references.                              |
|  <a href="#">ExtWhereUsed</a>   | Gets the links to external document that reference this document.                                |
|  <a href="#">HasPDF</a>         | Gets whether this drawing document has a PDF file in the vault.                                  |
|  <a href="#">IsTopLevel</a>     | Gets whether this document is at the top-level project.                                          |
|  <a href="#">Name</a>           | Gets or sets the name of the document.                                                           |
|  <a href="#">Notes</a>          | Gets the notes associated with this document.                                                    |
|  <a href="#">Number</a>         | Gets the number of this document.                                                                |
|  <a href="#">Owner</a>          | Gets the current owner of this document, which may be different from the author of the document. |
|  <a href="#">project</a>        | Gets the name of the project to which this document belongs.                                     |
|  <a href="#">Properties</a>     | Gets the properties of this document.                                                            |
|  <a href="#">References</a>     | Gets the links to the documents referenced by this document.                                     |
|  <a href="#">Revision</a>       | Gets the revision for this document.                                                             |
|  <a href="#">RevisionLabels</a> | Gets the next suggested revisions for the document.                                              |
| <a href="#">Revisions</a>                                                                                          | Gets all of the revisions of this document, in order from the oldest to newest.                  |

|                                                                                   |                                   |                                                                                                                                          |
|-----------------------------------------------------------------------------------|-----------------------------------|------------------------------------------------------------------------------------------------------------------------------------------|
|   |                                   |                                                                                                                                          |
|  | <a href="#">Size</a>              | Gets the size (in bytes) of a document smaller than 2GB or the size that represents the 32 low-order bits of a document larger than 2GB. |
|  | <a href="#">SizeH</a>             | Gets the size that represents the 32 high-order bits of a document larger than 2GB.                                                      |
|  | <a href="#">SolidWorksVersion</a> | Gets the SOLIDWORKS version of the document.                                                                                             |
|  | <a href="#">UpdateStamp</a>       | Gets the date on which this document was last updated.                                                                                   |
|  | <a href="#">WhereUsed</a>         | Gets the links to the documents that reference this document.                                                                            |

[Top](#)

## Public Methods

| Name                                                                                                                     | Description                                                                                                                                                      |
|--------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|  <a href="#">AddNote</a>                | Adds a note to the document.                                                                                                                                     |
|  <a href="#">BumpRevision</a>           | Changes the revision number of the document.                                                                                                                     |
|  <a href="#">ChangeOwner</a>            | Changes the document's owner.                                                                                                                                    |
|  <a href="#">ChangeProject</a>          | Moves the document to the specified project.                                                                                                                     |
|  <a href="#">ChangeStatus</a>           | Changes the lifecycle status of the document to the specified lifecycle status.                                                                                  |
|  <a href="#">GetDocumentSize</a>        | Gets the size (in bytes) of the document.                                                                                                                        |
|  <a href="#">GetEmbeddedEDWAsBase64</a> | Gets embedded eDrawing data with Base64 encoding, if available.                                                                                                  |
|  <a href="#">GetStatus</a>              | Gets the lifecycle status of the document.                                                                                                                       |
|  <a href="#">ReleaseOwnership</a>       | Allows you to release ownership of a document.                                                                                                                   |
|  <a href="#">Save</a>                   | Copies the document.                                                                                                                                             |
|  <a href="#">SaveAsPDF</a>              | Gets the PDF file for this drawing document from the vault, if the setting to create a PDF file of a drawing document in the vault during check-in was selected. |
|  <a href="#">SaveEmbeddedEDW</a>      | Saves the eDrawings embedded in the SOLIDWORKS document, if one exists.                                                                                          |
|  <a href="#">TakeOwnership</a>        | Allows you to take ownership of a document.                                                                                                                      |

[Top](#)

## See Also

[IPDMWDocument Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocuments Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## IPDMWDocument Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocument Interface

For a list of all members of this type, see [IPDMWDocument members](#).

## Public Properties

| Name                                                                                                               | Description                                                                |
|--------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------|
|  <a href="#">Attachments</a>    | Gets the non-SOLIDWORKS attachments for this SOLIDWORKS document.          |
|  <a href="#">Configurations</a> | Gets the configurations available for the specified document and revision. |
|  <a href="#">DateModified</a>   | Gets the date and time that this document was last modified.               |
|  <a href="#">Description</a>    | Gets the description of the document.                                      |
|  <a href="#">ExtReferences</a>  | Gets the links to external documents that this document references.        |
|  <a href="#">ExtWhereUsed</a>   | Gets the links to external document that reference this document.          |
|  <a href="#">HasPDF</a>         | Gets whether this drawing document has a PDF file in the vault.            |
|  <a href="#">IsTopLevel</a>     | Gets whether this document is at the top-level project.                    |

|                                                                                   |                                   |                                                                                                                                          |
|-----------------------------------------------------------------------------------|-----------------------------------|------------------------------------------------------------------------------------------------------------------------------------------|
|  | <a href="#">Name</a>              | Gets or sets the name of the document.                                                                                                   |
|  | <a href="#">Notes</a>             | Gets the notes associated with this document.                                                                                            |
|  | <a href="#">Number</a>            | Gets the number of this document.                                                                                                        |
|  | <a href="#">Owner</a>             | Gets the current owner of this document, which may be different from the author of the document.                                         |
|  | <a href="#">project</a>           | Gets the name of the project to which this document belongs.                                                                             |
|  | <a href="#">Properties</a>        | Gets the properties of this document.                                                                                                    |
|  | <a href="#">References</a>        | Gets the links to the documents referenced by this document.                                                                             |
|  | <a href="#">Revision</a>          | Gets the revision for this document.                                                                                                     |
|  | <a href="#">RevisionLabels</a>    | Gets the next suggested revisions for the document.                                                                                      |
|  | <a href="#">Revisions</a>         | Gets all of the revisions of this document, in order from the oldest to newest.                                                          |
|  | <a href="#">Size</a>              | Gets the size (in bytes) of a document smaller than 2GB or the size that represents the 32 low-order bits of a document larger than 2GB. |
|  | <a href="#">SizeH</a>             | Gets the size that represents the 32 high-order bits of a document larger than 2GB.                                                      |
|  | <a href="#">SolidWorksVersion</a> | Gets the SOLIDWORKS version of the document.                                                                                             |
|  | <a href="#">UpdateStamp</a>       | Gets the date on which this document was last updated.                                                                                   |
|  | <a href="#">WhereUsed</a>         | Gets the links to the documents that reference this document.                                                                            |

[Top](#)

## See Also

[IPDMWDocument Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocuments Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## AddNote Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : AddNote Method (IPDMWDocument)

Adds a note to the document.

## .NET Syntax

### Visual Basic (Declaration)

```
Function AddNote( _
    ByVal action As System.String, _
    ByVal note As System.String _
) As System.Integer
```

### Visual Basic (Usage)

```
Dim instance As IPDMWDocument
Dim action As System.String
Dim note As System.String
Dim value As System.Integer

value = instance.AddNote(action, note)
```

### C#

```
System.int AddNote(
    System.string action,
    System.string note
)
```

### C++/CLI

```
System.int AddNote(
    & System.String^ action,
```



Copy Code

```
& System.String^ note  
)
```

#### Parameters

*action*  
Action

*note*  
Note

#### Return Value

0 if successful, non-0 if not

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::AddNote](#).

### Remarks

The note is added to the document history and includes the name of the current user and the time when the user added the note.

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::Notes Property](#)

### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Attachments Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Attachments Property (IPDMWDocument)

Gets the non-SOLIDWORKS attachments for this SOLIDWORKS document.

### .NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Attachments As PDMWLinks
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As PDMWLinks
```

```
value = instance.Attachments
```

C#

```
PDMWLinks Attachments {get;}
```

C++/CLI

```
property PDMWLinks^ Attachments {  
    PDMWLinks^ get();  
}
```

#### Property Value

Collection of [links](#) of non-SOLIDWORKS attachments for this SOLIDWORKS document

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Attachments](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## BumpRevision Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : BumpRevision Method (IPDMWDocument)

Changes the revision number of the document.

## .NET Syntax

### Visual Basic (Declaration)

```
Function BumpRevision( _  
    ByVal i\_cstrNewRev As System.String, _  
    ByVal i\_cstrNote As System.String _  
) As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim i_cstrNewRev As System.String  
Dim i_cstrNote As System.String  
Dim value As System.Integer  
  
value = instance.BumpRevision(i_cstrNewRev, i_cstrNote)
```

### C#

```
System.int BumpRevision(  
    System.string i\_cstrNewRev,  
    System.string i\_cstrNote  
)
```

### C++/CLI

```
System.int BumpRevision(  
& System.String^ i\_cstrNewRev,  
& System.String^ i\_cstrNote  
)
```

### Parameters

*i\_cstrNewRev*  
New revision number

**NOTE:** If you specify an empty string for *i\_cstrNewRev*, then the next logical revision is used.

*i\_cstrNote*  
Note

### Return Value

0 on success, non-0 on failure

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::BumpRevision](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::Revision Property](#)  
[IPDMWDocument::RevisionLabels Property](#)  
[IPDMWLink::Revision Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2006 SP4

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## ChangeOwner Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks.Namespace](#) > [IPDMWDocument Interface](#) : ChangeOwner Method (IPDMWDocument)

Changes the document's owner.

## .NET Syntax

### Visual Basic (Declaration)

```
Function ChangeOwner( _  
    ByVal Owner As System.String _  
) As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim Owner As System.String  
Dim value As System.Integer  
  
value = instance.ChangeOwner(Owner)
```

### C#

```
System.int ChangeOwner(  
    System.string Owner  
)
```

### C++/CLI

```
System.int ChangeOwner(  
    & System.String^ Owner  
)
```

### Parameters

*Owner*  
Name of new document owner

### Return Value

0 on success, non-0 on failure

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::ChangeOwner](#).

## Remarks

This functionality is only available via the SOLIDWORKS Workgroup PDM API; it is not available in the user interface. Only vault administrators can use this method.

This method does not release ownership of any child documents. Use [IPDMWDocument::ReleaseOwnership](#) to do this.

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::ReleaseOwnership Method](#)  
[IPDMWDocument::TakeOwnership Method](#)

## Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## ChangeProject Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : ChangeProject Method (IPDMWDocument)

Moves the document to the specified project.

## .NET Syntax

### Visual Basic (Declaration)

```
Sub ChangeProject( _  
    ByVal project As System.String, _  
    ByVal bSelectedItem As System.Boolean, _  
    ByVal i\_childrenType As PDMWChildrenType, _  
    ByVal bIgnoreLinks As System.Boolean _  
)
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim project As System.String  
Dim bSelectedItem As System.Boolean  
Dim i_childrenType As PDMWChildrenType  
Dim bIgnoreLinks As System.Boolean  
  
instance.ChangeProject(project, bSelectedItem, i_childrenType, bIgnoreLinks)
```

### C#

```
void ChangeProject(  
    System.string project,  
    System.bool bSelectedItem,  
    PDMWChildrenType i\_childrenType,  
    System.bool bIgnoreLinks  
)
```

### C++/CLI

```
void ChangeProject(  
& System.String^ project,  
& System.bool bSelectedItem,  
& PDMWChildrenType i\_childrenType,  
& System.bool bIgnoreLinks  
)
```

### Parameters

*project*

Project to which to move the document

*bSelectedItem*

TRUE to move document, FALSE to not

*i\_childrenType*

Type of children documents, as defined in [PDMWChildrenType](#), to move to the new project

*bIgnoreLinks*

TRUE to ignore any references from other projects to the document, FALSE to not

### Return Value

True to ignore any references from other projects to the document, false to not

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::ChangeProject](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## ChangeStatus Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : ChangeStatus Method (IPDMWDocument)

Changes the lifecycle status of the document to the specified lifecycle status.

## .NET Syntax

### Visual Basic (Declaration)

```
Function ChangeStatus( _  
    ByVal i\_bstrStatus As System.String _  
) As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim i_bstrStatus As System.String  
Dim value As System.Integer  
  
value = instance.ChangeStatus(i_bstrStatus)
```

### C#

```
System.int ChangeStatus(  
    System.string i\_bstrStatus  
)
```

### C++/CLI

```
System.int ChangeStatus(  
& System.String^ i\_bstrStatus  
)
```

### Parameters

*i\_bstrStatus*

Value corresponding to one of the life-cycle statuses created in VaultAdmin

### Return Value

0 if successful, non-0 if not

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::ChangeStatus](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWConnection::Statuses Property](#)  
[IPDMWDocument::GetStatus Method](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

## Configurations Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Configurations Property (IPDMWDocument)

Gets the configurations available for the specified document and revision.

### .NET Syntax

Visual Basic (Declaration)

ReadOnly Property Configurations As PDMWConfigurations

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As PDMWConfigurations

value = instance.Configurations
```

C#

```
PDMWConfigurations Configurations {get;}
```

C++/CLI

```
property PDMWConfigurations^ Configurations {
    PDMWConfigurations^ get();
}
```

#### Property Value

Collection of [configurations](#)

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Configurations](#).

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

## DateModified Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : DateModified Property (IPDMWDocument)

Gets the date and time that this document was last modified.

### .NET Syntax

Visual Basic (Declaration)

Property DateModified As System.Object

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.Object

instance.DateModified = value
```

```
value = instance.DateModified
```

C#

```
System.Object DateModified {get; set;}
```

C++/CLI

```
property System.Object^ DateModified {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

#### Property Value

Date and time document last modified

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::DateModified](#).

### Remarks

For Visual Basic for Applications (VBA) and unmanaged C++ COM, this property returns a VARIANT of type VT\_DATE that corresponds to the Windows date-modified field: date, hours, minutes, seconds.

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::UpdateStamp Property](#)

### Availability

SOLIDWORKS Workgroup PDM 2006 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Description Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Description Property (IPDMWDocument)

Gets the description of the document.

### .NET Syntax

Visual Basic (Declaration)

```
Property Description As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.String
```

```
instance.Description = value
```

```
value = instance.Description
```

C#

```
System.string Description {get; set;}
```

C++/CLI

```
property System.String^ Description {  
    System.String^ get();
```

```
void set ( & System.String^ value);  
}
```

#### Property Value

Description of document

#### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Description](#).

#### Remarks

You can change the document's description property by accessing the document's custom property; for example, [IPDMWDocument::Properties](#)("Description").

#### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

#### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

### ExtReferences Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : ExtReferences Property (IPDMWDocument)

Gets the links to external documents that this document references.

#### .NET Syntax

##### Visual Basic (Declaration)

```
ReadOnly Property ExtReferences As PDMWLinks
```

##### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As PDMWLinks
```

```
value = instance.ExtReferences
```

##### C#

```
PDMWLinks ExtReferences {get;}
```

##### C++/CLI

```
property PDMWLinks^ ExtReferences {  
    PDMWLinks^ get();  
}
```

#### Property Value

Collection of [links](#) of external documents that this document references

#### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::ExtReferences](#).

#### Remarks

An external document is any type of derived part, parent or child, including base, mirrored, and component parts.

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument:ExtWhereUsed Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## ExtWhereUsed Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : ExtWhereUsed Property (IPDMWDocument)

Gets the links to external document that reference this document.

## .NET Syntax

### Visual Basic (Declaration)

ReadOnly Property ExtWhereUsed As PDMWLinks

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As PDMWLinks
```

```
value = instance.ExtWhereUsed
```

### C#

```
PDMWLinks ExtWhereUsed {get;}
```

### C++/CLI

```
property PDMWLinks^ ExtWhereUsed {  
    PDMWLinks^ get();  
}
```

### Property Value

Collection of [links](#) of external documents that reference this document

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument:ExtWhereUsed](#).

## Remarks

An external document is any type of derived part, parent or child, including base, mirrored, and component parts.

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument:ExtReferences Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## GetDocumentSize Method (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : GetDocumentSize Method (IPDMWDocument)

Gets the size (in bytes) of the document.

 .NET Syntax

Visual Basic (Declaration)

Function GetDocumentSize() As System.Object

Visual Basic (Usage)

Dim instance As [IPDMWDocument](#)  
Dim value As System.Object  
  
value = instance.GetDocumentSize()

C#

System.object GetDocumentSize()

C++/CLI

System.Object^ GetDocumentSize();

**Return Value**

Size (in bytes) of the document (see **Remarks**)

 Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::GetDocumentSize](#).

 Example

[Get Size of Document Larger Than 2GB \(VBA\)](#)

 Remarks

Convert the return value to a double. See the example for details.

 See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::Size Property](#)  
[IPDMWDocument::SizeH Property](#)

 Availability

SOLIDWORKS Workgroup PDM 2013 FCS

SOLIDWORKS Workgroup PDM API Help [Send comments on this topic.](#)

**GetEmbeddedEDWAsBase64 Method (IPDMWDocument)**

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : GetEmbeddedEDWAsBase64 Method (IPDMWDocument)

Gets embedded eDrawing data with Base64 encoding, if available.

 .NET Syntax

Visual Basic (Declaration)

Function GetEmbeddedEDWAsBase64() As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.String

value = instance.GetEmbeddedEDWAsBase64()
```

C#

```
System.string GetEmbeddedEDWAsBase64()
```

C++/CLI

```
System.String^ GetEmbeddedEDWAsBase64();
```

#### Return Value

Embedded eDrawing data with Base64 encoding

#### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::GetEmbeddedEDWAsBase64](#).

#### Remarks

Data can then be formatted inline into the eDrawing ActiveX control to display within a web page or HTML-formatted email.

Saving a SOLIDWORKS document with embedded eDrawings data is not supported in SOLIDWORKS 2006 and later, because eDrawings can now read native SOLIDWORKS files. This method only returns data for files with embedded eDrawings data created in SOLIDWORKS 2005 and earlier.

#### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::SaveEmbeddedEDW Method](#)

#### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

### GetStatus Method (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : GetStatus Method (IPDMWDocument)

Gets the lifecycle status of the document.

#### .NET Syntax

Visual Basic (Declaration)

```
Function GetStatus() As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.String

value = instance.GetStatus()
```

C#

```
System.string GetStatus()
```

C++/CLI

```
System.String^ GetStatus();
```

## Return Value

Lifecycle status

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::GetStatus](#).

## Example

[Extract Embedded eDrawings Data \(VBA\)](#)

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::ChangeStatus Method](#)  
[IPDMWConnection::Statuses Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## HasPDF Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks.Namespace](#) > [IPDMWDocument Interface](#) : HasPDF Property (IPDMWDocument)

Gets whether this drawing document has a PDF file in the vault.

## .NET Syntax

### Visual Basic (Declaration)

```
ReadOnly Property HasPDF As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.Integer

value = instance.HasPDF
```

### C#

```
System.int HasPDF {get;}
```

### C++/CLI

```
property System.int HasPDF {
    System.int get();
}
```

## Property Value

0 if this drawing document does not have a PDF file in the vault, 1 if it does

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::HasPDF](#).

## Remarks

Call [IPDMWDocument::SaveAsPDF](#) to get the PDF file of the drawing document from the vault, if it exists.

## See Also

## Availability

SOLIDWORKS Workgroup PDM 2008 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

### IsTopLevel Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : IsTopLevel Property (IPDMWDocument)

Gets whether this document is at the top-level project.

## .NET Syntax

### Visual Basic (Declaration)

```
ReadOnly Property IsTopLevel As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.Integer  
  
value = instance.IsTopLevel
```

### C#

```
System.int IsTopLevel {get;}
```

### C++/CLI

```
property System.int IsTopLevel {  
    System.int get();  
}
```

### Property Value

0 if document is at the top-level project, 1 if not

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::IsTopLevel](#).

## See Also

## Availability

SOLIDWORKS Workgroup PDM 2004 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

### Name Property (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Name Property (IPDMWDocument)

Gets or sets the name of the document.

## .NET Syntax

### Visual Basic (Declaration)

```
Property Name As System.String
```

### Visual Basic (Usage)

```
Dim instance As IPDMWDocument
Dim value As System.String

instance.Name = value

value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {
    System.String^ get();
    void set ( & System.String^ value);
}
```

#### Property Value

Name of document

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Name](#).

### Example

[Extract Embedded eDrawings Data \(VBA\)](#)  
[List Assemblies Where Part Used \(VBA\)](#)

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Notes Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Notes Property (IPDMWDocument)

Gets the notes associated with this document.

### .NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Notes As PDMWDocumentNotes
```

Visual Basic (Usage)

```
Dim instance As IPDMWDocument
Dim value As PDMWDocumentNotes

value = instance.Notes
```

C#

```
PDMWDocumentNotes Notes {get;}
```

C++/CLI

```
property PDMWDocumentNotes^ Notes {  
    PDMWDocumentNotes^ get();  
}
```

#### Property Value

Collection of [notes](#) associated with this document

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Notes](#).

### Remarks

Notes are ordered from oldest to newest.

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::AddNote Method](#)

### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Number Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Number Property (IPDMWDocument)

Gets the number of this document.

### .NET Syntax

#### Visual Basic (Declaration)

```
Property Number As System.String
```

#### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.String
```

```
instance.Number = value
```

```
value = instance.Number
```

#### C#

```
System.string Number {get; set;}
```

#### C++/CLI

```
property System.String^ Number {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

#### Property Value

Number of document

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Number](#).

## Remarks

You can change the document's number property by accessing the document's custom property; for example, [IPDMWDocument::Properties](#)("Number").

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Owner Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Owner Property (IPDMWDocument)

Gets the current owner of this document, which may be different from the author of the document.

## .NET Syntax

### Visual Basic (Declaration)

Property Owner As System.String

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.String
```

```
instance.Owner = value
```

```
value = instance.Owner
```

### C#

```
System.string Owner {get; set;}
```

### C++/CLI

```
property System.String^ Owner {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

### Property Value

Name of the current owner of this document

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Owner](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## project Property (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : project Property (IPDMWDocument)

Gets the name of the project to which this document belongs.

## .NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property project As System.String
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.String  
  
value = instance.project
```

C#

```
System.string project {get;}
```

C++/CLI

```
property System.String^ project {  
    System.String^ get();  
}
```

### Property Value

Name of project to which this document belongs

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::project](#).

## Example

[Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWProject Interface](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

## Properties Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Properties Property (IPDMWDocument)

Gets the properties of this document.

## .NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Properties As PDMWProperties
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As PDMWProperties
```

```
value = instance.Properties
```

C#

```
PDMWProperties Properties {get;}
```

C++/CLI

```
property PDMWProperties^ Properties {  
    PDMWProperties^ get();  
}
```

#### Property Value

Collection of [properties](#)

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Properties](#).

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::Description Property](#)  
[IPDMWDocument::Number Property](#)

### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

## References Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : References Property (IPDMWDocument)

Gets the links to the documents referenced by this document.

### .NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property References As PDMWLinks
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As PDMWLinks
```

```
value = instance.References
```

C#

```
PDMWLinks References {get;}
```

C++/CLI

```
property PDMWLinks^ References {  
    PDMWLinks^ get();  
}
```

#### Property Value

Collection of [links](#) to documents referenced by this document

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::References](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## ReleaseOwnership Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : ReleaseOwnership Method (IPDMWDocument)

Allows you to release ownership of a document.

## .NET Syntax

### Visual Basic (Declaration)

```
Function ReleaseOwnership() As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.Integer
```

```
value = instance.ReleaseOwnership()
```

### C#

```
System.int ReleaseOwnership()
```

### C++/CLI

```
System.int ReleaseOwnership();
```

### Return Value

0 if successful, non-0 if not

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::ReleaseOwnership](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::ChangeOwner Method](#)  
[IPDMWDocument::TakeOwnership Method](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 SP3

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Revision Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Revision Property (IPDMWDocument)

Gets the revision for this document.

## .NET Syntax

### Visual Basic (Declaration)

## Property Revision As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.String
```

```
instance.Revision = value
```

```
value = instance.Revision
```

C#

```
System.string Revision {get; set;}
```

C++/CLI

```
property System.String^ Revision {
    System.String^ get();
    void set ( & System.String^ value);
}
```

### Property Value

Revision for this document

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Revision](#).

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::BumpRevision Method](#)  
[IPDMWDocument::RevisionLabels Property](#)  
[IPDMWDocument::Revisions Property](#)

### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## RevisionLabels Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : RevisionLabels Property (IPDMWDocument)

Gets the next suggested revisions for the document.

### .NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property RevisionLabels As System.Object
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.Object
```

```
value = instance.RevisionLabels
```

C#

```
System.object RevisionLabels {get;}
```

C++/CLI

```
property System.Object^ RevisionLabels {  
    System.Object^ get();  
}
```

#### Property Value

Revisions

#### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::RevisionLabels](#).

#### Requirements

For example, if the current revision labels are PRE-01, DEV-01, and REL-01, the next suggested revision labels would be PRE-02, DEV-02, and REL-02.

Call this property before calling [IPDMWConnection::Checkin](#).

#### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::BumpRevision Method](#)  
[IPDMWDocument::Revision Property](#)  
[IPDMWDocument::Revisions Property](#)

#### Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

### Revisions Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Revisions Property (IPDMWDocument)

Gets all of the revisions of this document, in order from the oldest to newest.

#### .NET Syntax

Visual Basic (Declaration)

ReadOnly Property Revisions As PDMWDocuments

Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As PDMWDocuments  
  
value = instance.Revisions
```

C#

```
PDMWDocuments Revisions {get;}
```

C++/CLI

```
property PDMWDocuments^ Revisions {  
    PDMWDocuments^ get();  
}
```

#### Property Value

Collection of the revisions of this [document](#)

#### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Revisions](#).

## Remarks

The collection returned is indexed by number as well as revision, but not by the name of the document. Therefore, the following is possible:

```
' VBA
' Given a PDMWDocuments collection called doc
dim doc2 as PDMWDocument
Dim revs As PDMWDocuments
Set revs = doc.Revisions
Set doc2 = revs ('01') ' Pass a revision name string as an argument
```

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::BumpRevision Method](#)  
[IPDMWDocument::Revision Property](#)  
[IPDMWDocument::RevisionLabels Property](#)  
[IPDMWLink::Revision Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Save Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Save Method (IPDMWDocument)

Copies the document.

## .NET Syntax

### Visual Basic (Declaration)

```
Function Save( _
    Optional ByVal saveDir As System.String _
) As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim saveDir As System.String
Dim value As System.Integer

value = instance.Save(saveDir)
```

### C#

```
System.int Save(
    System.string saveDir
)
```

### C++/CLI

```
System.int Save(
    & System.String^ saveDir
)
```

## Parameters

*saveDir*

Name of the folder to which to copy the document

## Return Value

0 if successful, non-0 if not

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Save](#).

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::SaveAsPDF Method](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## SaveAsPDF Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : SaveAsPDF Method (IPDMWDocument)

Gets the PDF file for this drawing document from the vault, if the setting to create a PDF file of a drawing document in the vault during check-in was selected.

## .NET Syntax

Visual Basic (Declaration)

```
Function SaveAsPDF( _  
    Optional ByVal saveDir As System.String _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim saveDir As System.String  
Dim value As System.Integer
```

```
value = instance.SaveAsPDF(saveDir)
```

C#

```
System.int SaveAsPDF(  
    System.string saveDir  
)
```

C++/CLI

```
System.int SaveAsPDF(  
& System.String^ saveDir  
)
```

## Parameters

*saveDir*  
Folder where to save the PDF file

## Return Value

0 if the PDF file is found in the vault, non-0 if not

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::SaveAsPDF](#).

## Remarks

Before calling this method, call [IPDMWDocument::HasPDF](#) to determine if a PDF file of the drawing document exists in the vault.

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2008 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments](#) on this topic.

## SaveEmbeddedEDW Method (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : SaveEmbeddedEDW Method (IPDMWDocument)

Saves the eDrawings embedded in the SOLIDWORKS document, if one exists.

## .NET Syntax

### Visual Basic (Declaration)

```
Function SaveEmbeddedEDW( _  
    ByVal saveFileName As System.String _  
) As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim saveFileName As System.String  
Dim value As System.Integer  
  
value = instance.SaveEmbeddedEDW(saveFileName)
```

### C#

```
System.int SaveEmbeddedEDW(  
    System.string saveFileName  
)
```

### C++/CLI

```
System.int SaveEmbeddedEDW(  
& System.String^ saveFileName  
)
```

### Parameters

*saveFileName*  
Filename or folder to which to save the embedded eDrawings

### Return Value

0 if successful, non-0 if not

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::SaveEmbeddedEDW](#).

## Example

[Extract Embedded eDrawings Data \(VBA\)](#)

## Remarks

Saving a SOLIDWORKS document with embedded eDrawings data is not supported in SOLIDWORKS 2006 and later, because eDrawings can now read native SOLIDWORKS files. This method only returns data for files with embedded eDrawings data created in SOLIDWORKS 2005 and earlier.

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::GetEmbeddedEDWAsBase64 Method](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Size Property (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : Size Property (IPDMWDocument)

Gets the size (in bytes) of a document smaller than 2GB or the size that represents the 32 low-order bits of a document larger than 2GB.

## .NET Syntax

### Visual Basic (Declaration)

ReadOnly Property Size As System.Integer

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.Integer
```

```
value = instance.Size
```

### C#

```
System.int Size {get;}
```

### C++/CLI

```
property System.int Size {
    System.int get();
}
```

### Property Value

Size (in bytes) of a document smaller than 2GB or the size that represents the 32 low-order bits of a document larger than 2GB (see **Remarks**)

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::Size](#).

## Example

[Get Size of Document Larger Than 2GB \(VBA\)](#)

## Remarks

| To get the size of a document... | Call...                                                                                |
|----------------------------------|----------------------------------------------------------------------------------------|
| Smaller than 2GB                 | this property                                                                          |
| Larger than 2GB                  | this property and <a href="#">IPDMWDocument::SizeH</a> and combine their return values |
| Any size                         | <a href="#">IPDMWDocument::GetDocumentSize</a>                                         |

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

# SizeH Property (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : SizeH Property (IPDMWDocument)

Gets the size that represents the 32 high-order bits of a document larger than 2GB.

## Visual Basic Syntax

Visual Basic (Declaration)

ReadOnly Property SizeH As System.Integer

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.Integer
```

```
value = instance.SizeH
```

C#

```
System.int SizeH {get;}
```

C++/CLI

```
property System.int SizeH {
    System.int get();
}
```

### Property Value

Size that represents the 32 high-order bits of a document larger than 2GB (see **Remarks**)

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::SizeH](#).

## Example

[Get Size of Document Larger Than 2GB \(VBA\)](#)

## Remarks

To get the size of a document...

Call...

Smaller than 2GB

[IPDMWDocument.Size](#)

Larger than 2GB

this property and IPDMWDocument.Size and combine their return values

Any size

[IPDMWDocument.GetDocumentSize](#)

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2013 FCS

# SolidWorksVersion Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : SolidWorksVersion Property (IPDMWDocument)

Gets the SOLIDWORKS version of the document.

## Visual Basic Syntax

### Visual Basic (Declaration)

ReadOnly Property SolidWorksVersion As System.Integer

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.Integer
```

```
value = instance.SolidWorksVersion
```

### C#

```
System.int SolidWorksVersion {get;}
```

### C++/CLI

```
property System.int SolidWorksVersion {  
    System.int get();  
}
```

### Property Value

SOLIDWORKS version

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::SOLIDWORKSVersion](#).

## Remarks

| Major SOLIDWORKS Release | Version Number |
|--------------------------|----------------|
| SOLIDWORKS 95            | 44             |
| SOLIDWORKS 96            | 243            |
| SOLIDWORKS 97            | 483            |
| SOLIDWORKS 97Plus        | 629            |
| SOLIDWORKS 98            | 822            |
| SOLIDWORKS 98Plus        | 1008           |
| SOLIDWORKS 99            | 1137           |
| SOLIDWORKS 2000          | 1500           |
| SOLIDWORKS 2001          | 1750           |
| SOLIDWORKS 2001Plus      | 1950           |
| SOLIDWORKS 2003          | 2200           |
| SOLIDWORKS 2004          | 2500           |
| SOLIDWORKS 2005          | 2800           |
| SOLIDWORKS 2006          | 3100           |
| SOLIDWORKS 2007          | 3400           |
| SOLIDWORKS 2008          | 3800           |
| SOLIDWORKS 2009          | 4100           |

|                 |       |
|-----------------|-------|
| SOLIDWORKS 2010 | 4400  |
| SOLIDWORKS 2011 | 4700  |
| SOLIDWORKS 2012 | 5000  |
| SOLIDWORKS 2013 | 6000  |
| SOLIDWORKS 2014 | 7000  |
| SOLIDWORKS 2015 | 8000  |
| SOLIDWORKS 2016 | 9000  |
| SOLIDWORKS 2017 | 10000 |

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2005 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## TakeOwnership Method (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : TakeOwnership Method (IPDMWDocument)

Allows you to take ownership of a document.

## .NET Syntax

Visual Basic (Declaration)

```
Function TakeOwnership() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocument
Dim value As System.Integer

value = instance.TakeOwnership()
```

C#

```
System.int TakeOwnership()
```

C++/CLI

```
System.int TakeOwnership();
```

### Return Value

0 if successful, an exception is thrown if not (see **Remarks**)

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::TakeOwnership](#).

## Remarks

Before you can check a document in, you must own it. See [IPDMWConnection::Checkin](#) for details about checking in documents.

If a call to this method fails, the **Document ownership was denied exception** is thrown. You can trap this exception using a try/catch block in C# or C++, or On Error in VB.

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::ChangeOwner Method](#)  
[IPDMWDocument::ReleaseOwnership Method](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## UpdateStamp Property (IPDMWDocument)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : UpdateStamp Property (IPDMWDocument)

Gets the date on which this document was last updated.

## .NET Syntax

### Visual Basic (Declaration)

```
ReadOnly Property UpdateStamp As System.Integer
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As System.Integer  
  
value = instance.UpdateStamp
```

### C#

```
System.int UpdateStamp {get;}
```

### C++/CLI

```
property System.int UpdateStamp {  
    System.int get();  
}
```

### Property Value

Date document last updated

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::UpdateStamp](#).

## Remarks

The update stamp is an integer representing the time stamp. The update stamp in a SOLIDWORKS document is incremented when:

- the state of the model changes (for example, you suppress or unsuppress a feature in a part or an assembly)
- the geometry changes (for example, any action that requires a rebuild)

This time stamp is not incremented for such operations as color changes, feature or configuration name changes, and so on.

This property returns 0 for non-SOLIDWORKS documents.

## See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)  
[IPDMWDocument::DateModified Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2004 FCS

## WhereUsed Property (IPDMWDocument)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocument Interface](#) : WhereUsed Property (IPDMWDocument)

Gets the links to the documents that reference this document.

### .NET Syntax

#### Visual Basic (Declaration)

ReadOnly Property WhereUsed As PDMWLinks

#### Visual Basic (Usage)



```
Dim instance As IPDMWDocument  
Dim value As PDMWLinks
```

```
value = instance.WhereUsed
```

#### C#

```
PDMWLinks WhereUsed {get;}
```

#### C++/CLI

```
property PDMWLinks^ WhereUsed {  
    PDMWLinks^ get();  
}
```

#### Property Value

Collection of [links](#) to the documents that reference this document

### Visual Basic for Applications (VBA) Syntax

See [PDMWDocument::WhereUsed](#).

### Example

[List Assemblies Where Part Used \(VBA\)](#)

### See Also

[IPDMWDocument Interface](#)  
[IPDMWDocument Members](#)

### Availability

SOLIDWORKS Workgroup PDM 2003 FCS

# IPDMWDocumentNote (Type)

## IPDMWDocumentNote Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocumentNote Interface

Provides access to notes.

**NOTE:** Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

**.NET Syntax**

Visual Basic (Declaration)

Public Interface IPDMWDocumentNote

Visual Basic (Usage)

Dim instance As [IPDMWDocumentNote](#)

C#

public interface IPDMWDocumentNote

C++/CLI

public interface class IPDMWDocumentNote

**Visual Basic for Applications (VBA) Syntax**

See [PDMWDocumentNote](#).

**Remarks**

A note object corresponds to an entry in the **History/Notes** tab in a document's **SOLIDWORKS Workgroup PDM - Document Information** dialog box in the SOLIDWORKS Workgroup PDM Client.

**Accessors**

[IPDMWDocumentsNotes::Item](#)

**See Also**

[IPDMWDocumentNote Members](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocumentNotes Interface](#)

## IPDMWDocumentNote Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocumentNote Interface

The following tables list the members exposed by [IPDMWDocumentNote](#).

**Public Properties**

| Name                        | Description                                                               |
|-----------------------------|---------------------------------------------------------------------------|
| <a href="#">action</a>      | Gets the description of the SOLIDWORKS Workgroup PDM event that occurred. |
| <a href="#">DateTime</a>    | Gets the date and time of the note associated with this document.         |
| <a href="#">Description</a> | Gets the description for this note.                                       |
| <a href="#">user</a>        | Gets the name of the user who created this note.                          |

[Top](#)

## See Also

[IPDMWDocumentNote Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocumentNotes Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## IPDMWDocumentNote Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocumentNote Interface

For a list of all members of this type, see [IPDMWDocumentNote members](#).

## Public Properties

| Name                                                                                                          | Description                                                               |
|---------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------|
|  <a href="#">action</a>      | Gets the description of the SOLIDWORKS Workgroup PDM event that occurred. |
|  <a href="#">DateTime</a>    | Gets the date and time of the note associated with this document.         |
|  <a href="#">Description</a> | Gets the description for this note.                                       |
|  <a href="#">user</a>        | Gets the name of the user who created this note.                          |

[Top](#)

## See Also

[IPDMWDocumentNote Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocumentNotes Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## action Property (IPDMWDocumentNote)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocumentNote Interface](#) : action Property (IPDMWDocumentNote)

Gets the description of the SOLIDWORKS Workgroup PDM event that occurred.

## .NET Syntax

Visual Basic (Declaration)

Property action As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWDocumentNote  
Dim value As System.String
```

```
instance.action = value
```

```
value = instance.action
```

C#

```
System.string action {get; set;}
```

C++/CLI

```
property System.String^ action {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

### Property Value

Event that occurred

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocumentNote::action](#).

## Remarks

The return value can contain:

- "Check In"
- "Check Out"
- "Take Ownership"
- "Release Ownership"
- "Change Project"

## See Also

[IPDMWDocumentNote Interface](#)  
[IPDMWDocumentNote Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## DateTime Property (IPDMWDocumentNote)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocumentNote Interface](#) : DateTime Property (IPDMWDocumentNote)

Gets the date and time of the note associated with this document.

## .NET Syntax

Visual Basic (Declaration)

Property DateTime As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWDocumentNote  
Dim value As System.String
```

```
instance.DateTime = value
```

```
value = instance.DateTime
```

C#

```
System.string DateTime {get; set;}
```

C++/CLI

```
property System.String^ DateTime {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

### Property Value

Date and time of the note associated with this document

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocumentNote::DateTime](#).

## See Also

[IPDMWDocumentNote Interface](#)  
[IPDMWDocumentNote Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Description Property (IPDMWDocumentNote)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocumentNote Interface](#) : Description Property (IPDMWDocumentNote)

Gets the description for this note.

## .NET Syntax

Visual Basic (Declaration)

Property Description As System.String

Visual Basic (Usage)



```
Dim instance As IPDMWDocumentNote
Dim value As System.String
```

```
instance.Description = value
```

```
value = instance.Description
```

C#

```
System.string Description {get; set;}
```

C++/CLI

```
property System.String^ Description {
    System.String^ get();
    void set ( & System.String^ value);
}
```

### Property Value

Description for this note

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocumentNote::Description](#).

## See Also

[IPDMWDocumentNote Interface](#)  
[IPDMWDocumentNote Members](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## user Property (IPDMWDocumentNote)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocumentNote Interface](#) : user Property (IPDMWDocumentNote)

Gets the name of the user who created this note.

## .NET Syntax

Visual Basic (Declaration)

Property user As System.String

```
Dim instance As IPDMWDocumentNote  
Dim value As System.String  
  
instance.user = value  
  
value = instance.user
```

C#

```
System.string user {get; set;}
```

C++/CLI

```
property System.String^ user {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

**Property Value**

Name of the user who created this note

 **Visual Basic for Applications (VBA) Syntax**

See [PDMWDocumentNote::user](#).

 **See Also**

[IPDMWDocumentNote Interface](#)  
[IPDMWDocumentNote Members](#)

 **Availability**

SOLIDWORKS Workgroup PDM 2003 FCS

# IPDMWDocumentNotes (Type)

## IPDMWDocumentNotes Interface

[See Also](#) [Members](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocumentNotes Interface

Contains [IPDMWDocumentNote](#) objects.

**NOTE:** Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

**.NET Syntax**

Visual Basic (Declaration)

Public Interface IPDMWDocumentNotes

Visual Basic (Usage)

Dim instance As [IPDMWDocumentNotes](#)

C#

public interface IPDMWDocumentNotes

C++/CLI

public interface class IPDMWDocumentNotes

**Visual Basic for Applications (VBA) Syntax**

See [PDMWDocumentNotes](#).

**Accessors**

[IPDMWDocument::Notes](#)

**See Also**

[IPDMWDocumentNotes Members](#)  
[PDMWorks.Interop.pdmworks Namespace](#)

## IPDMWDocumentNotes Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocumentNotes Interface

The following tables list the members exposed by [IPDMWDocumentNotes](#).

**Public Properties**

| Name                  | Description                                 |
|-----------------------|---------------------------------------------|
| <a href="#">Count</a> | Gets the number of notes for this document. |
| <a href="#">Item</a>  | Gets the specified notes for this document. |

[Top](#)

**See Also**

[IPDMWDocumentNotes Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)

## IPDMWDocumentNotes Interface Properties

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocumentNotes Interface

For a list of all members of this type, see [IPDMWDocumentNotes members](#).

## Public Properties

| Name                                                                                                    | Description                                 |
|---------------------------------------------------------------------------------------------------------|---------------------------------------------|
|  <a href="#">Count</a> | Gets the number of notes for this document. |
|  <a href="#">Item</a>  | Gets the specified notes for this document. |

[Top](#)

## See Also

[IPDMWDocumentNotes Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Count Property (IPDMWDocumentNotes)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocumentNotes Interface](#) : Count Property (IPDMWDocumentNotes)

Gets the number of notes for this document.

## .NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Count As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IPDMWDocumentNotes  
Dim value As System.Integer  
  
value = instance.Count
```

C#

```
System.int Count {get;}
```

C++/CLI

```
property System.int Count {  
    System.int get();  
}
```

### Property Value

Number of notes for this document

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocumentNotes::Count](#).

## See Also

[IPDMWDocumentNotes Interface](#)  
[IPDMWDocumentNotes Members](#)  
[IPDMWDocumentNotes::Item Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Item Property (IPDMWDocumentNotes)

[See Also](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocumentNotes Interface](#) : Item Property (IPDMWDocumentNotes)

Gets the specified notes for this document.

## .NET Syntax

### Visual Basic (Declaration)

```
ReadOnly Default Property Item( _  
    ByVal Index As System.Object _  
) As System.Object
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocumentNotes  
Dim Index As System.Object  
Dim value As System.Object  
  
value = instance.Item(Index)
```

### C#

```
System.object this[  
    System.object Index  
]; {get;}
```

### C++/CLI

```
property System.Object^ default [System.Object^] {  
    System.Object^ get(System.Object^ Index);  
}
```

### Parameters

*Index*

Number indicating which note to get

### Property Value

[IPDMWDocumentNote](#)

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocumentNotes::Item](#).

## See Also

[IPDMWDocumentNotes Interface](#)

[IPDMWDocumentNotes Members](#)

[IPDMWDocumentNotes::Count Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 SP3

# IPDMWDocuments (Type)

## IPDMWDocuments Interface

[See Also](#) [Members](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocuments Interface

Contains [IPDMWDocument](#) objects.

**NOTE:** Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

**.NET Syntax**

Visual Basic (Declaration)

Public Interface IPDMWDocuments

Visual Basic (Usage)

Dim instance As [IPDMWDocuments](#)

C#

public interface IPDMWDocuments

C++/CLI

public interface class IPDMWDocuments

**Visual Basic for Applications (VBA) Syntax**

See [PDMWDocuments](#).

**Example**

[Extract Embedded eDrawings Data \(VBA\)](#)  
[Get Specific Document \(VBA\)](#)  
[List Assemblies Where Part Used \(VBA\)](#)  
[Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

**Accessors**

[IPDMWConnection::Documents](#)  
[IPDMWProject::Documents](#)

**See Also**

[IPDMWDocuments Members](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocument Interface](#)

## IPDMWDocuments Interface Members

[See Also](#) [Properties](#)



[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocuments Interface

The following tables list the members exposed by [IPDMWDocuments](#).

**Public Properties**

| Name                  | Description                   |
|-----------------------|-------------------------------|
| <a href="#">Count</a> | Gets the number of documents. |
| <a href="#">Item</a>  | Gets the specified document.  |

## See Also

[IPDMWDocuments Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocument Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## IPDMWDocuments Interface Properties

[See Also](#)

[PDMWorks.Interop.pdmworks Namespace](#) : IPDMWDocuments Interface

For a list of all members of this type, see [IPDMWDocuments members](#).

## Public Properties

| Name                                                                                                    | Description                   |
|---------------------------------------------------------------------------------------------------------|-------------------------------|
|  <a href="#">Count</a> | Gets the number of documents. |
|  <a href="#">Item</a>  | Gets the specified document.  |

[Top](#)

## See Also

[IPDMWDocuments Interface](#)  
[PDMWorks.Interop.pdmworks Namespace](#)  
[IPDMWDocument Interface](#)

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Count Property (IPDMWDocuments)

[See Also](#) [Example](#)

[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocuments Interface](#) : Count Property (IPDMWDocuments)

Gets the number of documents.

## .NET Syntax

Visual Basic (Declaration)

ReadOnly Property Count As System.Integer

Visual Basic (Usage)



```
Dim instance As IPDMWDocuments  
Dim value As System.Integer  
  
value = instance.Count
```

C#

```
System.int Count {get;}
```

C++/CLI

```
property System.int Count {  
    System.int get();  
}
```

### Property Value

Number of documents

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocuments::Count](#).

## Example

[Get Names of Projects for All Documents in Vault \(VB.NET\)](#)

## See Also

[IPDMWDocuments Interface](#)  
[IPDMWDocuments Members](#)  
[IPDMWDocuments::Item Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS

SOLIDWORKS Workgroup PDM API Help

[Send comments on this topic.](#)

## Item Property (IPDMWDocuments)

[See Also](#) [Example](#)



[PDMWorks.Interop.pdmworks Namespace](#) > [IPDMWDocuments Interface](#) : Item Property (IPDMWDocuments)

Gets the specified document.

## .NET Syntax

### Visual Basic (Declaration)

```
ReadOnly Default Property Item( _  
    ByVal Index As System.Object _  
) As System.Object
```

### Visual Basic (Usage)



```
Dim instance As IPDMWDocuments  
Dim Index As System.Object  
Dim value As System.Object
```

```
value = instance.Item(Index)
```

### C#

```
System.object this[  
    System.object Index  
]; {get;}
```

### C++/CLI

```
property System.Object^ default [System.Object^] {  
    System.Object^ get(System.Object^ Index);  
}
```

### Parameters

*Index*

Number or name indicating which document to get (see **Remarks**)

### Property Value

[IPDMWDocument](#)

## Visual Basic for Applications (VBA) Syntax

See [PDMWDocuments::Item](#).

## Example

[Get Specific Document \(VBA\)](#)

## Remarks

If this collection was returned from [IPDMWDocument::References](#), then the document name refers to its revision name string, not its document name string.

## See Also

[IPDMWDocuments Interface](#)  
[IPDMWDocuments Members](#)  
[IPDMWDocuments::Count Property](#)

## Availability

SOLIDWORKS Workgroup PDM 2003 FCS