

SOLIDWORKS API (.NET VBA C#) — Reference (249/337): ISelectionMgr (part 1 of 2)

SOLIDWORKS API Documentation (converted from CHM)

ISelectionMgr (part 1 of 2) (Type)

ISelectionMgr Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISelectionMgr Interface

Allows you to get information about selected objects, obtain API objects representing the selected item, and get your selection coordinates interpreted in model or sketch space.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISelectionMgr
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
```

C#

```
public interface ISelectionMgr
```

C++/CLI

```
public interface class ISelectionMgr
```

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr](#).

Example

[Create Imported Surface Body From Sketch \(C#\)](#)
[Access Assembly \(C++\)](#)
[Get Object's Persistent Reference ID \(C++\)](#)
[Get Spline Points \(C++\)](#)
[Insert BOM Table \(VBA\)](#)
[Create Equation-driven Curve \(VB.NET\)](#)
[Create Equation-driven Curve \(C#\)](#)
[Create Equation-driven Curve \(VBA\)](#)
[Add Objects to Selection List \(VBA\)](#)
[Add Objects to Selection List \(VB.NET\)](#)
[Add Objects to Selection List \(C#\)](#)

Accessors

[IModelDoc2::SelectionManager](#)

Access Diagram

[SelectionMgr](#)

See Also

[ISelectionMgr Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISelectData Interface](#)

ISelectionMgr Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISelectionMgr Interface

For a list of all members of this type, see [ISelectionMgr members](#).

Public Methods

Name	Description
 AddSelectionListObject	Adds the specified object to the selection list.
 AddSelectionListObjects	Adds the specified objects to the selection list.
 ClearSelectionColors	Clears all of selection color settings.
 CreateCallout	Obsolete. Superseded by ISelectionMgr.CreateCallout2
 CreateCallout2	Creates a callout for the selection.
 CreateSelectData	Creates a ISelectData object to use as argument with Select methods.
 DeSelect	Obsolete. Superseded by ISelectionMgr.DeSelect2
 DeSelect2	Deselects the specified entity.
 GetPreSelectedObject	Gets the preselected object when the preselection notify event is fired.
 GetSelectByIdSpecification	Gets the selection specification for the specified object.
 GetSelectedCoordSysElement	Gets the selected coordinate system element.
 GetSelectedObject	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6
 GetSelectedObject2	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6
 GetSelectedObject3	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6
 GetSelectedObject4	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6
 GetSelectedObject5	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6
 GetSelectedObject6	Gets the selected object.
 GetSelectedObjectCount	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectCount2
 GetSelectedObjectCount2	Gets the number of selected objects.
 GetSelectedObjectLoop	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectLoop2
 GetSelectedObjectLoop2	Gets the loop, if selected, for the selected edge.
 GetSelectedObjectMark	Gets the value of the mark for the specified selection.
 GetSelectedObjectsComponent	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectsComponent3
 GetSelectedObjectsComponent2	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectsComponent3
 GetSelectedObjectsComponent3	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectsComponent4
 GetSelectedObjectsComponent4	Gets the selected component in an assembly or drawing.
 GetSelectedObjectsDrawingView	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectsDrawingView2
 GetSelectedObjectsDrawingView2	Gets the drawing view for the selected object.
 GetSelectedObjectsFace	Gets the face of the specified selection if the specified selection is a silhouette edge .
 GetSelectedObjectType	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectType3
 GetSelectedObjectType2	Obsolete. Superseded by ISelectionMgr.GetSelectedObjectType3
 GetSelectedObjectType3	Gets the type of object selected.
 GetSelectionPoint	Obsolete. Superseded by ISelectionMgr.GetSelectionPoint2
 GetSelectionPoint2	Gets the selected point in model space coordinates from the currently selected object.
 GetSelectionPointInSketchSpace	Obsolete. Superseded by ISelectionMgr.GetSelectionPointInSketchSpace2
 GetSelectionPointInSketchSpace2	Gets the selection point projected on to the active sketch and returned in sketch space.
 GetSelectionSpecification	Gets the selection specification at the specified index of the current selection list.
 IDeSelect	Obsolete. Superseded by ISelectionMgr.IDeSelect2
 IDeSelect2	Deselects the specified entity.
 IGetSelectedObject	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6
 IGetSelectedObject2	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6
 IGetSelectedObject3	Obsolete. Superseded by ISelectionMgr.GetSelectedObject6

	IGetSelectedObject4	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	IGetSelectedObjectsComponent	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsComponent3 .
	IGetSelectedObjectsComponent2	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsComponent3 .
	IGetSelectionPoint	Obsolete. Superseded by ISelectionMgr::IGetSelectionPoint2 .
	IGetSelectionPoint2	Gets the selected point in model space coordinates from the currently selected object.
	IGetSelectionPointInSketchSpace	Obsolete. Superseded by ISelectionMgr::IGetSelectionPointInSketchSpace2 .
	IGetSelectionPointInSketchSpace2	Gets the selection point projected on to the active sketch and returned in sketch space.
	IsCoordSysElementSelected	Gets whether the selection is a coordinate system element.
	IsInEditTarget	Obsolete. Superseded by ISelectionMgr::IsInEditTarget2 .
	IsInEditTarget2	Gets whether the selected object is in the edit target.
	ResumeSelectionList	Obsolete. Superseded by ISelectionMgr::ResumeSelectionList2 .
	ResumeSelectionList2	Reinstates the previously suspended selection list.
	SetCallout	Adds a callout to the currently selected object.
	SetSelectedObjectMark	Sets the mark value for the specified selection.
	SetSelectionPoint	Obsolete. Superseded by ISelectionMgr::SetSelectionPoint2 .
	SetSelectionPoint2	Sets the selection point in model space.
	SuspendSelectionList	Suspends the current selection list.

[Top](#)

See Also

[ISelectionMgr Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISelectData Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISelectionMgr Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISelectionMgr Interface

The following tables list the members exposed by [ISelectionMgr](#).

Public Properties

Name	Description
 EnableContourSelection	Enables and disables contour selection.
 EnableSelection	Enables or disables selection.
 SelectionColor	Gets or sets the selection color.

[Top](#)

Public Methods

Name	Description
 AddSelectionListObject	Adds the specified object to the selection list.
 AddSelectionListObjects	Adds the specified objects to the selection list.
 ClearSelectionColors	Clears all of selection color settings.
 CreateCallout	Obsolete. Superseded by ISelectionMgr::CreateCallout2 .
 CreateCallout2	Creates a callout for the selection.
 CreateSelectData	Creates a ISelectData object to use as argument with Select methods.
 DeSelect	Obsolete. Superseded by ISelectionMgr::DeSelect2 .
 DeSelect2	Deselects the specified entity.

		
	GetPreSelectedObject	Gets the preselected object when the preselection notify event is fired.
	GetSelectByIdSpecification	Gets the selection specification for the specified object.
	GetSelectedCoordSysElement	Gets the selected coordinate system element.
	GetSelectedObject	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	GetSelectedObject2	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	GetSelectedObject3	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	GetSelectedObject4	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	GetSelectedObject5	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	GetSelectedObject6	Gets the selected object.
	GetSelectedObjectCount	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectCount2 .
	GetSelectedObjectCount2	Gets the number of selected objects.
	GetSelectedObjectLoop	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectLoop2 .
	GetSelectedObjectLoop2	Gets the loop, if selected, for the selected edge.
	GetSelectedObjectMark	Gets the value of the mark for the specified selection.
	GetSelectedObjectsComponent	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsComponent3 .
	GetSelectedObjectsComponent2	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsComponent3 .
	GetSelectedObjectsComponent3	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsComponent4 .
	GetSelectedObjectsComponent4	Gets the selected component in an assembly or drawing.
	GetSelectedObjectsDrawingView	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsDrawingView2 .
	GetSelectedObjectsDrawingView2	Gets the drawing view for the selected object.
	GetSelectedObjectsFace	Gets the face of the specified selection if the specified selection is a silhouette edge .
	GetSelectedObjectType	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectType3 .
	GetSelectedObjectType2	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectType3 .
	GetSelectedObjectType3	Gets the type of object selected.
	GetSelectionPoint	Obsolete. Superseded by ISelectionMgr::GetSelectionPoint2 .
	GetSelectionPoint2	Gets the selected point in model space coordinates from the currently selected object.
	GetSelectionPointInSketchSpace	Obsolete. Superseded by ISelectionMgr::GetSelectionPointInSketchSpace2 .
	GetSelectionPointInSketchSpace2	Gets the selection point projected on to the active sketch and returned in sketch space.
	GetSelectionSpecification	Gets the selection specification at the specified index of the current selection list.
	IDeSelect	Obsolete. Superseded by ISelectionMgr::IDeSelect2 .
	IDeSelect2	Deselects the specified entity.
	IGetSelectedObject	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	IGetSelectedObject2	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	IGetSelectedObject3	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	IGetSelectedObject4	Obsolete. Superseded by ISelectionMgr::GetSelectedObject6 .
	IGetSelectedObjectsComponent	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsComponent3 .
	IGetSelectedObjectsComponent2	Obsolete. Superseded by ISelectionMgr::GetSelectedObjectsComponent3 .
	IGetSelectionPoint	Obsolete. Superseded by ISelectionMgr::IGetSelectionPoint2 .
	IGetSelectionPoint2	Gets the selected point in model space coordinates from the currently selected object.
	IGetSelectionPointInSketchSpace	Obsolete. Superseded by ISelectionMgr::IGetSelectionPointInSketchSpace2 .
	IGetSelectionPointInSketchSpace2	Gets the selection point projected on to the active sketch and returned in sketch space.
	IsCoordSysElementSelected	Gets whether the selection is a coordinate system element.

		
	IsInEditTarget	Obsolete. Superseded by ISelectionMgr.IsInEditTarget2 .
	IsInEditTarget2	Gets whether the selected object is in the edit target.
	ResumeSelectionList	Obsolete. Superseded by ISelectionMgr.ResumeSelectionList2 .
	ResumeSelectionList2	Reinstates the previously suspended selection list.
	SetCallout	Adds a callout to the currently selected object.
	SetSelectedObjectMark	Sets the mark value for the specified selection.
	SetSelectionPoint	Obsolete. Superseded by ISelectionMgr.SetSelectionPoint2 .
	SetSelectionPoint2	Sets the selection point in model space.
	SuspendSelectionList	Suspends the current selection list.

[Top](#)

 See Also

[ISelectionMgr Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISelectData Interface](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISelectionMgr Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISelectionMgr Interface

For a list of all members of this type, see [ISelectionMgr members](#).

 Public Properties

Name	Description
 EnableContourSelection	Enables and disables contour selection.
 EnableSelection	Enables or disables selection.
 SelectionColor	Gets or sets the selection color.

[Top](#)

 See Also

[ISelectionMgr Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISelectData Interface](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

AddSelectionListObject Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : AddSelectionListObject Method (ISelectionMgr)

Adds the specified object to the selection list.

 .NET Syntax

Visual Basic (Declaration)

```
Function AddSelectionListObject( _
    ByVal Object As System.Object, _
    ByVal SelectData As System.Object _
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As ISelectionMgr
Dim Object As System.Object
Dim SelectData As System.Object
```



```
Dim value As System.Boolean
```

```
value = instance.AddSelectionListObject(Object, SelectData)
```

C#

```
System.bool AddSelectionListObject(  
    System.object Object,  
    System.object SelectData  
)
```

C++/CLI

```
System.bool AddSelectionListObject(  
& System.Object^ Object,  
& System.Object^ SelectData  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Object

Object to add to the selection list (see **Remarks**)

SelectData

[ISelectData](#)

Return Value

True if successful, false if not

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::AddSelectionListObject](#).

Example

[Insert Indent Feature \(C#\)](#)
[Insert Indent Feature \(VB.NET\)](#)
[Insert Indent Feature \(VBA\)](#)

Remarks

Call [ISelectionMgr::CreateSelectData](#) to specify SelectData.

To add objects to a selection list without pre-selecting the objects in the user interface:

1. Call [ISelectionMgr::SuspendSelectionList](#) to suspend the current selection list, preserving its contents and starting a new selection list.
2. Call [ISelectionMgr::AddSelectionListObject](#) or [ISelectionMgr::AddSelectionListObjects](#) to populate the new selection list.
3. Process the objects in the new selection list.
4. Call [ISelectionMgr::ResumeSelectionList](#) to reinstate the suspended selection list.

To programmatically pre-select objects in the user interface and add them to a selection list, use [IModelDocExtension::SelectByID2](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionSetItem::GetCorrespondingItem Method \(\)](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

AddSelectionListObjects Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : AddSelectionListObjects Method (ISelectionMgr)

Adds the specified objects to the selection list.

.NET Syntax

Visual Basic (Declaration)

```
Function AddSelectionListObjects( _
    ByVal Objects As System.Object, _
    ByVal SelectData As System.Object _
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim Objects As System.Object
Dim SelectData As System.Object
Dim value As System.Integer

value = instance.AddSelectionListObjects(Objects, SelectData)
```

C#

```
System.int AddSelectionListObjects(
    System.object Objects,
    System.object SelectData
)
```

C++/CLI

```
System.int AddSelectionListObjects(
    & System.Object^ Objects,
    & System.Object^ SelectData
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Objects
Array of objects to add to the selection list (see **Remarks**)
SelectData
[ISelectData](#)

Return Value

Number of objects added to the selection list

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::AddSelectionListObjects](#).

Example

[Add Objects to Selection List \(VBA\)](#)
[Add Objects to Selection List \(VB.NET\)](#)
[Add Objects to Selection List \(C#\)](#)

Remarks

For VB.NET and C# applications, specify Objects as an array of System.Runtime.InteropServices.DispatchWrappers. See the examples and [IDispatch Object Arrays as Input in .NET](#) for more information.

Call [ISelectionMgr::CreateSelectData](#) to specify SelectData.

To add objects to a selection list without preselecting the objects in the user interface:

1. Call [ISelectionMgr::SuspendSelectionList](#) to suspend the current selection list, preserving its contents and starting a new selection list.
2. Call [ISelectionMgr::AddSelectionListObject](#) or [ISelectionMgr::AddSelectionListObjects](#) to populate a new selection list.
3. Process the objects in the new selection list.
4. Call [ISelectionMgr::ResumeSelectionList](#) to reinstate the suspended selection list.

To programmatically preselect objects in the user interface and add them to a selection list, use [IModelDocExtension::SelectByID2](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionSetItem::GetCorrespondingItem Method \(\)](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ClearSelectionColors Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : ClearSelectionColors Method (ISelectionMgr)

Clears all of selection color settings.

.NET Syntax

Visual Basic (Declaration)

```
Sub ClearSelectionColors()
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
instance.ClearSelectionColors()
```

C#

```
void ClearSelectionColors()
```

C++/CLI

```
void ClearSelectionColors();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::ClearSelectionColors](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::SelectionColor Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateCallout Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : CreateCallout Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::CreateCallout2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateCallout() As Callout
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim value As Callout

value = instance.CreateCallout()
```

C#

```
Callout CreateCallout()
```

C++/CLI

```
Callout^ CreateCallout();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::CreateCallout](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateCallout2 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : CreateCallout2 Method (ISelectionMgr)

Creates a callout for the selection.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateCallout2( _
    ByVal NumberOfRows As System.Integer, _
    ByVal LpHandler As System.Object _
) As Callout
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim NumberOfRows As System.Integer
Dim LpHandler As System.Object
Dim value As Callout
```

```
value = instance.CreateCallout2(NumberOfRows, LpHandler)
```

C#

```
Callout CreateCallout2(
    System.int NumberOfRows,
    System.object LpHandler
)
```

C++/CLI

```
Callout^ CreateCallout2(
    & System.int NumberOfRows,
    & System.Object^ LpHandler
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

NumberOfRows
Number of rows in the callout

LpHandler

Pointer to the event handler for the callout ([ISwCalloutHandler](#))

Return Value

[Callout](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::CreateCallout2](#).

Example

[Create Multi-row Callouts \(VBA\)](#)

Remarks

To create a callout independent of a selection, use [IModelDocExtension::CreateCallout](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::SetCallout Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateSelectData Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : CreateSelectData Method (ISelectionMgr)

Creates a [ISelectData](#) object to use as argument with Select methods.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateSelectData() As SelectData
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim value As SelectData
```

```
value = instance.CreateSelectData()
```

C#

```
SelectData CreateSelectData()
```

C++/CLI

```
SelectData^ CreateSelectData();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[ISelectData](#) object

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::CreateSelectData](#).

Example

[Check Interference Using IAssemblyDoc::ToolsCheckInterference2 \(VBA\)](#)
[Create Plane Thru 3 Points In-context \(VBA\)](#)
[Get Faces Associated with Feature \(VBA\)](#)
[Insert DXF File and Add Dimension \(VBA\)](#)
[Select Loop of Edges \(VBA\)](#)
[Use Safe Entity \(VBA\)](#)
[Select Multiple Objects for Selection Boxes \(C#\)](#)
[Select Multiple Objects for Selection Boxes \(VB.NET\)](#)
[Select Multiple Objects for Selection Boxes \(VBA\)](#)
[Select Edges of All Holes on Face \(C#\)](#)
[Select Edges of All Holes on Face \(VB.NET\)](#)
[Select Edges of All Holes on Face \(VBA\)](#)

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeSelect Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : DeSelect Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::DeSelect2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function DeSelect( _  
    ByVal AtIndex As System.Object _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Object  
Dim value As System.Integer
```

```
value = instance.DeSelect(AtIndex)
```

C#

```
System.int DeSelect(  
    System.object AtIndex  
)
```

C++/CLI

```
System.int DeSelect(  
& System.Object^ AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::DeSelect](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

DeSelect2 Method (ISelectionMgr)

[See Also](#) [Example](#)[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : DeSelect2 Method (ISelectionMgr)

Deselects the specified entity.

.NET Syntax

Visual Basic (Declaration)

```
Function DeSelect2(
    ByVal AtIndex As System.Object, _
    ByVal Mark As System.Integer _
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim AtIndex As System.Object
Dim Mark As System.Integer
Dim value As System.Integer

value = instance.DeSelect2(AtIndex, Mark)
```

C#

```
System.int DeSelect2(
    System.object AtIndex,
    System.int Mark
)
```

C++/CLI

```
System.int DeSelect2(
    & System.Object^ AtIndex,
    & System.int Mark
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

*AtIndex*Index position within the current list of selected items where index ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)*Mark*

- 1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

1 if the specified entity is deselected, 0 if not

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::DeSelect2](#).

Example

[Deselect Marked Entity \(C#\)](#)
[Deselect Marked Entity \(VB.NET\)](#)
[Deselect Marked Entity \(VBA\)](#)

Remarks

If running SOLIDWORKS x64, then you must declare AtIndex as a Long in VBA.

AtIndex should be either an array of 32-bit integers or a single 32-bit integer. See [Long vs. Integer](#) for details about data types.

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectCount2 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

EnableContourSelection Property (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : EnableContourSelection Property (ISelectionMgr)

Enables and disables contour selection.

.NET Syntax

Visual Basic (Declaration)

```
Property EnableContourSelection As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim value As System.Boolean  
  
instance.EnableContourSelection = value  
  
value = instance.EnableContourSelection
```

C#

```
System.bool EnableContourSelection {get; set;}
```

C++/CLI

```
property System.bool EnableContourSelection {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to enable contour selection, false to disable it

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::EnableContourSelection](#).

Example

[Enable Contour Selection \(VBA\)](#)
[Enable Contour Selection \(VB.NET\)](#)
[Enable Contour Selection \(C#\)](#)

Remarks

This property enables you to select regions that are defined by single, multiple, open, or closed sketch boundaries. See the SOLIDWORKS Help for more information about selecting contours.

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::EnableSelection Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

EnableSelection Property (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : EnableSelection Property (ISelectionMgr)

Enables or disables selection.

.NET Syntax

Visual Basic (Declaration)

Property EnableSelection As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim value As System.Boolean
```

```
instance.EnableSelection = value
```

```
value = instance.EnableSelection
```

C#

```
System.bool EnableSelection {get; set;}
```

C++/CLI

```
property System.bool EnableSelection {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True if selection is enabled, false if disabled

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::EnableSelection](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::EnableContourSelection Property](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetPreSelectedObject Method (ISelectionMgr)

[See Also](#) [Example](#)



Gets the preselected object when the preselection notify event is fired.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPreSelectedObject() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim value As System.Object  
  
value = instance.GetPreSelectedObject()
```

C#

```
System.object GetPreSelectedObject()
```

C++/CLI

```
System.Object^ GetPreSelectedObject();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Preselected object

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetPreSelectedObject](#).

Example

[Get Preselected Object \(C#\)](#)
[Get Preselected Object \(VB.NET\)](#)
[Get Preselected Object \(VBA\)](#)

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[DAssemblyDocEvents UserSelectionPreNotifyEventHandler Delegate](#)
[DDrawingDocEvents UserSelectionPreNotifyEventHandler Delegate](#)
[DPartDocEvents UserSelectionPreNotifyEventHandler Delegate](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectByIdSpecification Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectByIdSpecification Method (ISelectionMgr)

Gets the selection specification for the specified object.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectByIdSpecification( _  
    ByVal Object As System.Object, _  
    ByRef SelectByString As System.String, _  
    ByRef ObjectType As System.String, _  
    ByRef Type As System.Integer _  
) As System.Boolean
```

```

Dim instance As ISelectionMgr
Dim Object As System.Object
Dim SelectByString As System.String
Dim ObjectType As System.String
Dim Type As System.Integer
Dim value As System.Boolean

value = instance.GetSelectByIdSpecification(Object, SelectByString, ObjectType, Type)

```

C#

```

System.bool GetSelectByIdSpecification(
    System.object Object,
    out System.string SelectByString,
    out System.string ObjectType,
    out System.int Type
)

```

C++/CLI

```

System.bool GetSelectByIdSpecification(
    & System.Object^ Object,
    & [Out] System.String^ SelectByString,
    & [Out] System.String^ ObjectType,
    & [Out] System.int Type
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Object

Object for which to get the selection specification

SelectByString

Feature name of Object; "" if Object is not a feature

ObjectType

Type of Object

Type

Type of Object as defined in [swSelectType_e](#)

Return Value

True if successful, false if not

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectByIdSpecification](#).

Example

[Get Selection Specification \(VBA\)](#)

[Get Selection Specification \(VB.NET\)](#)

[Get Selection Specification \(C#\)](#)

See Also

[ISelectionMgr Interface](#)

[ISelectionMgr Members](#)

[ISelectionMgr::GetSelectionSpecification Method \(\)](#)

[ISelectionMgr::GetSelectedObject6 Method \(\)](#)

[IModelDocExtension::SelectById2 Method \(\)](#)

[IFeature::GetNameForSelection Method \(\)](#)

[ISelectionMgr::GetSelectedObjectLoop2 Method \(\)](#)

[ISelectionMgr::GetSelectedObjectMark Method \(\)](#)

[ISelectionMgr::GetSelectedObjectsComponent4 Method \(\)](#)

[ISelectionMgr::GetSelectedObjectsDrawingView2 Method \(\)](#)

[ISelectionMgr::GetSelectedObjectType3 Method \(\)](#)

[ISelectionMgr::GetSelectionPoint2 Method \(\)](#)

[ISelectionMgr::GetSelectionPointInSketchSpace2 Method \(\)](#)

[ISelectionMgr::DeSelect2 Method \(\)](#)

[ISelectionMgr::GetSelectedObjectMark Method \(\)](#)

[ISelectionMgr::SetSelectionPoint2 Method \(\)](#)

Availability

GetSelectedCoordSysElement Method (ISelectionMgr)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedCoordSysElement Method (ISelectionMgr)

Gets the selected coordinate system element.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedCoordSysElement( _
    ByVal Index As System.Integer, _
    ByVal Mark As System.Integer _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim Index As System.Integer
Dim Mark As System.Integer
Dim value As System.Object

value = instance.GetSelectedCoordSysElement(Index, Mark)
```

C#

```
System.object GetSelectedCoordSysElement(
    System.int Index,
    System.int Mark
)
```

C++/CLI

```
System.Object^ GetSelectedCoordSysElement(
    & System.int Index,
    & System.int Mark
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

*Index*Index position within the current list of selected items, where Index ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)*Mark*

- 1 = All selections regardless of marks
- 0 = only the selections without marks

Any other value = Value that was used to mark and select an object

Return Value

[ICoordinateSystemElement](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedCoordSysElement](#).

Example

See the [ICoordinateSystemElement](#) examples.

Remarks

After calling this method, call [ISelectionMgr::IsCoordSysElementSelected](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

Availability

SOLIDWORKS 2025 SP01, Revision Number 33.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObject Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObject Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObject( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.GetSelectedObject(AtIndex)
```

C#

```
System.object GetSelectedObject(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectedObject(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObject](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObject2 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObject2 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObject2( _  
    ByVal AtIndex As System.Integer _
```

```
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.GetSelectedObject2(AtIndex)
```

C#

```
System.object GetSelectedObject2(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectedObject2(  
&    System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObject2](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSelectedObject3 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObject3 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObject3( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.GetSelectedObject3(AtIndex)
```

C#

```
System.object GetSelectedObject3(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectedObject3(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObject3](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSelectedObject4 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObject4 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObject4( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object
```

```
value = instance.GetSelectedObject4(AtIndex)
```

C#

```
System.object GetSelectedObject4(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectedObject4(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObject4](#).

See Also

GetSelectedObject5 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObject5 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObject5( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.GetSelectedObject5(AtIndex)
```

C#

```
System.object GetSelectedObject5(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectedObject5(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObject5](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

GetSelectedObject6 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObject6 Method (ISelectionMgr)

Gets the selected object.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObject6( _  
    ByVal Index As System.Integer, _  
    ByVal Mark As System.Integer _  
) As System.Object
```

```
Dim instance As ISelectionMgr
Dim Index As System.Integer
Dim Mark As System.Integer
Dim value As System.Object

value = instance.GetSelectedObject6(Index, Mark)
```

C#

```
System.Object GetSelectedObject6(
    System.int Index,
    System.int Mark
)
```

C++/CLI

```
System.Object^ GetSelectedObject6(
    & System.int Index,
    & System.int Mark
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position within the current list of selected items, where Index ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)

Mark

- 1 = All selections regardless of marks
- 0 = only the selections without marks

Any other value = Value that was used to mark and select an object

Return Value

Selected object as defined in [swSelectType](#) e; Nothing or null might be returned if the type is not supported or if nothing is selected

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObject6](#).

Example

[Access Assembly \(C++\)](#)
[Get Spline Points \(C++\)](#)
[Create Imported Surface Body from Sketch \(C#\)](#)
[Access Selections \(VBA\)](#)
[Get and Set Names of Note \(VBA\)](#)
[Get Custom Properties for Cut-list Item \(VBA\)](#)
[Insert BOM Table \(VBA\)](#)
[Replace Sketch Text \(VBA\)](#)
[Get Areas of MidSurface Faces \(C#\)](#)
[Get Areas of MidSurface Faces \(VB.NET\)](#)
[Get Areas of MidSurface Faces \(VBA\)](#)
[Get DimXpertManager Info \(VBA\)](#)
[Get DimXpertManager Info \(VB.NET\)](#)

Remarks

If...

Reference surfaces are selected

- Top-level item is selected in the DimXpertManager tab
- Non-top-level items are selected in the DimXpertManager tab
- Dimensions are selected

[ISelectionMgr](#) object obtained from a drawing document

ISelectionMgr object obtained from a part or assembly document

Then this method returns...

Reference surface faces instead of the entire reference surface feature.

- [IDimXpertManager](#) object.
- I-Feature object.
- [IDisplayDimension](#) object instead of the [IDimension](#) object.

Selected [IDrawingComponent](#) object.

[IComponent2](#) object.

If...

You specify -1 for the Index argument

Then this method returns...

The Mark argument is ignored and the dynamically highlighted entity is selected if dynamic highlighting is turned on. See also IAssemblyDoc event [DynamicHighlightNotify](#), IDrawingDoc event [DynamicHighlightNotify](#), and IPartDoc event [DynamicHighlightNotify](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::SetSelectedObjectMark Method](#)
[ISelectionMgr::SetSelectionPoint2 Method](#)
[IModelDocExtension::SelectById2 Method](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)
[IFeature::GetNameForSelection Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectCount Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectCount Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectCount2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim value As System.Integer  
  
value = instance.GetSelectedObjectCount()
```

C#

```
System.int GetSelectedObjectCount()
```

C++/CLI

```
System.int GetSelectedObjectCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectCount](#).

See Also

GetSelectedObjectCount2 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectCount2 Method (ISelectionMgr)

Gets the number of selected objects.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectCount2( _  
    ByVal Mark As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim Mark As System.Integer  
Dim value As System.Integer  
  
value = instance.GetSelectedObjectCount2(Mark)
```

C#

```
System.int GetSelectedObjectCount2(  
    System.int Mark  
)
```

C++/CLI

```
System.int GetSelectedObjectCount2(  
& System.int Mark  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Mark

- -1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

Number of selected objects

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectCount2](#).

Example

[Create Multi-row Callouts \(VBA\)](#)
[Selection Lists \(VBA\)](#)
[Create Library Feature With References \(C#\)](#)
[Create Library Feature With References \(VB.NET\)](#)
[Create Library Feature With References \(VBA\)](#)

Remarks

This method can be used to determine if a valid selection was made.

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IGetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectLoop Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectLoop Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectLoop2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectLoop( _  
    ByVal AtIndex As System.Integer _  
) As Loop2
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As Loop2
```

```
value = instance.GetSelectedObjectLoop(AtIndex)
```

C#

```
Loop2 GetSelectedObjectLoop(  
    System.int AtIndex  
)
```

C++/CLI

```
Loop2^ GetSelectedObjectLoop(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectLoop](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectLoop2 Method (ISelectionMgr)

[See Also](#)



Gets the loop, if selected, for the selected edge.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectLoop2( _
    ByVal Index As System.Integer, _
    ByVal Mark As System.Integer _
) As Loop2
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim Index As System.Integer
Dim Mark As System.Integer
Dim value As Loop2

value = instance.GetSelectedObjectLoop2(Index, Mark)
```

C#

```
Loop2 GetSelectedObjectLoop2(
    System.int Index,
    System.int Mark
)
```

C++/CLI

```
Loop2^ GetSelectedObjectLoop2(
    & System.int Index,
    & System.int Mark
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position within the current list of selected items, where AtIndex ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)

Mark

- -1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

[Loop](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectLoop2](#).

Remarks

The index starts at 1, even when using C++. However, if you specify -1 for the Index argument, then the Mark argument is ignored and the dynamically highlighted loop is selected if dynamic highlighting is turned on. See also IAssemblyDoc event [DynamicHighlightNotify](#), IDrawingDoc event [DynamicHighlightNotify](#), and IPartDoc event [DynamicHighlightNotify](#).

If a loop is not associated with an edge, then this method returns NULL.

NOTE: Use this method to find out if the selected edge has an associated loop. [IModelDoc2::SelectLoop](#) does not add an item to the [ISelectionMgr](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)

[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectMark Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectMark Method (ISelectionMgr)

Gets the value of the mark for the specified selection.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectMark( _  
    ByVal AtIndex As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Integer
```

```
value = instance.GetSelectedObjectMark(AtIndex)
```

C#

```
System.int GetSelectedObjectMark(  
    System.int AtIndex  
)
```

C++/CLI

```
System.int GetSelectedObjectMark(  
&    System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Index position within the current list of selected items where AtIndex ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#)

Return Value

Number used as a mark for the selected item; this number is used by certain API functions that require ordered entity selection

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectMark](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)

[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::IGetSelectionPointInSketchSpace2 Method](#)
[IModelDocExtension::SelectById2 Method](#)
[ISelectData::Mark Property](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)
[ISelectionMgr::SetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2001 FCS, Revision Number 9.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectsComponent Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectsComponent Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectsComponent3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectsComponent( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object
```

```
value = instance.GetSelectedObjectsComponent(AtIndex)
```

C#

```
System.object GetSelectedObjectsComponent(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectedObjectsComponent(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectsComponent](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectsComponent2 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectsComponent2 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectsComponent3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectsComponent2( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.GetSelectedObjectsComponent2(AtIndex)
```

C#

```
System.Object GetSelectedObjectsComponent2(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectedObjectsComponent2(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectsComponent2](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSelectedObjectsComponent3 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectsComponent3 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectsComponent4](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectsComponent3( _  
    ByVal Index As System.Integer, _  
    ByVal Mark As System.Integer _  
) As Component2
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim Index As System.Integer  
Dim Mark As System.Integer  
Dim value As Component2  
  
value = instance.GetSelectedObjectsComponent3(Index, Mark)
```

C#

```
Component2 GetSelectedObjectsComponent3(  
    System.int Index,  
    System.int Mark  
)
```

C++/CLI

```
Component2^ GetSelectedObjectsComponent3(  
& System.int Index,  
& System.int Mark  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position within the current list of selected items, where the index ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)

Mark

- -1 = All selections regardless of marks
- 0 = Only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

[Component](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectsComponent3](#).

Example

[Access Selections \(VBA\)](#)
[Add Comment to Assembly Component \(VBA\)](#)
[Align Assembly Component to Assembly Origin and Planes \(VBA\)](#)
[Display Temporary Body \(C#\)](#)
[Display Temporary Body \(VB.NET\)](#)
[Display Temporary Body \(VBA\)](#)

Remarks

The index starts at 1, even when using C++. However, if you specify -1 for the Index argument, then the Mark argument is ignored and the dynamically highlighted component is selected if dynamic highlighting is turned on. See also IAssemblyDoc event [DynamicHighlightNotify](#).

The difference between this obsolete method and [ISelectionMgr::GetSelectedObjectsComponent4](#) is that ISelectionMgr::GetSelectedObjectsComponent4 can return an [IDrawingComponent](#) and ISelectionMgr::GetSelectedObjectsComponent3 cannot

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::ISelectionMgr::IGetSelectionPointInSketchSpace2 Method](#)
[IComponent2::Select3 Method](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

Gets the selected component in an assembly or drawing.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectsComponent4( _
    ByVal Index As System.Integer, _
    ByVal Mark As System.Integer _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim Index As System.Integer
Dim Mark As System.Integer
Dim value As System.Object

value = instance.GetSelectedObjectsComponent4(Index, Mark)
```

C#

```
System.Object GetSelectedObjectsComponent4(
    System.int Index,
    System.int Mark
)
```

C++/CLI

```
System.Object^ GetSelectedObjectsComponent4(
    & System.int Index,
    & System.int Mark
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position within the current list of selected items, where the index ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)

Mark

- -1 = All selections regardless of marks
- 0 = Only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

[Component](#) or [Drawing component](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectsComponent4](#).

Example

[Move Assembly Components to New Folder \(C#\)](#)
[Move Assembly Components to New Folder \(VB.NET\)](#)
[Move Assembly Components to New Folder \(VBA\)](#)
[Select Drawing Component \(C#\)](#)
[Select Drawing Component \(VB.NET\)](#)
[Select Drawing Component \(VBA\)](#)

Remarks

The index starts at 1, even when using C++. However, if you specify -1 for the Index argument, then the Mark argument is ignored and the dynamically highlighted component is selected if dynamic highlighting is turned on. See also IAssemblyDoc event [DynamicHighlightNotify](#).

The difference between this method and the now obsolete [ISelectionMgr::GetSelectedObjectsComponent3](#) is that ISelectionMgr::GetSelectedObjectsComponent4 can return an [IDrawingComponent](#) and ISelectionMgr::GetSelectedObjectsComponent3 cannot

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::DeSelect2 Method \(\)](#)
[ISelectionMgr::GetSelectedObject6 Method \(\)](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method \(\)](#)
[ISelectionMgr::GetSelectedObjectMark Method \(\)](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method \(\)](#)
[ISelectionMgr::GetSelectedObjectType3 Method \(\)](#)
[ISelectionMgr::GetSelectionPoint2 Method \(\)](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method \(\)](#)
[ISelectionMgr::IDeSelect2 Method \(\)](#)
[ISelectionMgr::IGetSelectionPoint2 Method \(\)](#)
[ISelectionMgr::IGetSelectionPointInSketchSpace2 Method \(\)](#)
[IComponent2::Select4 Method \(\)](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2013 SP03, Revision Number 21.3

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectsDrawingView Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectsDrawingView Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectsDrawingView2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectsDrawingView( _  
    ByVal AtIndex As System.Integer _  
) As View
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As View
```

```
value = instance.GetSelectedObjectsDrawingView(AtIndex)
```

C#

```
View GetSelectedObjectsDrawingView(  
    System.int AtIndex  
)
```

C++/CLI

```
View^ GetSelectedObjectsDrawingView(  
&    System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectsDrawingView](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

GetSelectedObjectsDrawingView2 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectsDrawingView2 Method (ISelectionMgr)

Gets the drawing view for the selected object.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectsDrawingView2( _
    ByVal Index As System.Integer, _
    ByVal Mark As System.Integer _
) As View
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr
Dim Index As System.Integer
Dim Mark As System.Integer
Dim value As View

value = instance.GetSelectedObjectsDrawingView2(Index, Mark)
```

C#

```
View GetSelectedObjectsDrawingView2(
    System.int Index,
    System.int Mark
)
```

C++/CLI

```
View^ GetSelectedObjectsDrawingView2(
    & System.int Index,
    & System.int Mark
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position with in the current list of selected items, where AtIndex ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)

Mark

- -1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

[Drawing view](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectsDrawingView2](#).

Example

[Get Labels of Datum Origin \(C#\)](#)
[Get Labels of Datum Origin \(VB.NET\)](#)
[Get Labels of Datum Origin \(VBA\)](#)

Remarks

The index starts at 1, even when using C++. However, if you specify -1 for the Index argument, then the Mark argument is ignored and the dynamically highlighted view is selected if dynamic highlighting is turned on. See also IDrawingDoc event [DynamicHighlightNotify](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)
[ISelectionMgr::IGetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectedObjectsFace Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectsFace Method (ISelectionMgr)

Gets the face of the specified selection if the specified selection is a [silhouette edge](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectsFace( _  
    ByVal AtIndex As System.Integer, _  
    ByVal Mark As System.Integer _  
) As Face2
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim Mark As System.Integer  
Dim value As Face2
```

```
value = instance.GetSelectedObjectsFace(AtIndex, Mark)
```

C#

```
Face2 GetSelectedObjectsFace(  
    System.int AtIndex,  
    System.int Mark  
)
```

C++/CLI

```
Face2^ GetSelectedObjectsFace(  
& System.int AtIndex,  
& System.int Mark  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Index position within the current list of selected items, where AtIndex ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#)

Mark

- 1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

[Face](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectsFace](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSelectedObjectType Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectType Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectType3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectType( _  
    ByVal AtIndex As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Integer  
  
value = instance.GetSelectedObjectType(AtIndex)
```

C#

```
System.int GetSelectedObjectType(  
    System.int AtIndex  
)
```

C++/CLI

```
System.int GetSelectedObjectType(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectType](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSelectedObjectType2 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectType2 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObjectType3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectType2( _  
    ByVal AtIndex As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Integer  
  
value = instance.GetSelectedObjectType2(AtIndex)
```

C#

```
System.int GetSelectedObjectType2(  
    System.int AtIndex  
)
```

C++/CLI

```
System.int GetSelectedObjectType2(  
    & System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectType2](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSelectedObjectType3 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectedObjectType3 Method (ISelectionMgr)

Gets the type of object selected.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectedObjectType3( _  
    ByVal Index As System.Integer, _  
    ByVal Mark As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim Index As System.Integer
```

```
Dim Mark As System.Integer
Dim value As System.Integer

value = instance.GetSelectedObjectType3(Index, Mark)
```

C#

```
System.int GetSelectedObjectType3(
    System.int Index,
    System.int Mark
)
```

C++/CLI

```
System.int GetSelectedObjectType3(
    & System.int Index,
    & System.int Mark
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position with in the current list of selected items, where AtIndex ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**).

Mark

- -1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

Type of object as defined in [swSelectType_e](#)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectedObjectType3](#).

Example

[Get Dimension Tolerance \(VBA\)](#)
[Get Projected Point \(VBA\)](#)
[Insert Column in BOM Table \(C#\)](#)
[Insert Column in BOM Table \(VB.NET\)](#)
[Insert Column in BOM Table \(VBA\)](#)

Remarks

The index starts at 1, even when using C++. However, if you specify -1 for the Index argument, then the Mark argument is ignored and the dynamically highlighted view is selected if dynamic highlighting is turned on. See also IAssemblyDoc event [DynamicHighlightNotify](#), IDrawingDoc event [DynamicHighlightNotify](#), and IPartDoc event [DynamicHighlightNotify](#).

When reference surfaces are selected, this method returns swSelFACES instead of the entire swSelREFSURFACES feature.

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectCount2 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectsComponent2 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IGetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

GetSelectionPoint Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectionPoint Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectionPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectionPoint( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.GetSelectionPoint(AtIndex)
```

C#

```
System.object GetSelectionPoint(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectionPoint(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectionPoint](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectionPoint2 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectionPoint2 Method (ISelectionMgr)

Gets the selected point in model space coordinates from the currently selected object.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectionPoint2( _  
    ByVal Index As System.Integer, _  
    ByVal Mark As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```

Dim instance As ISelectionMgr
Dim Index As System.Integer
Dim Mark As System.Integer
Dim value As System.Object

value = instance.GetSelectionPoint2(Index, Mark)

```

C#

```

System.Object GetSelectionPoint2(
    System.int Index,
    System.int Mark
)

```

C++/CLI

```

System.Object^ GetSelectionPoint2(
    & System.int Index,
    & System.int Mark
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position with in the current list of selected items, where AtIndex ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)

Mark

- -1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

Array of 3 doubles (x,y,z)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectionPoint2](#).

Example

[Create Multi-row Callouts \(VBA\)](#)
[Create Drag Arrow Manipulator \(C#\)](#)
[Create Drag Arrow Manipulator \(VB.NET\)](#)
[Create Drag Arrow Manipulator \(VBA\)](#)

Remarks

The index starts at 1, even when using C++. However, if you specify -1 for the Index argument, then the Mark argument is ignored and the dynamically highlighted view is selected if dynamic highlighting is turned on. See also IAssemblyDoc event [DynamicHighlightNotify](#), IDrawingDoc event [DynamicHighlightNotify](#), and IPartDoc event [DynamicHighlightNotify](#).

The point returned from ISelectionMgr::GetSelectionPoint2 or [ISelectionMgr::IGetSelectionPoint2](#) cannot lie on the object that was selected. For example, the user can select an edge when the edge is within the pick radius of their mouse cursor. However, to get a point on a face, edge, or vertex, use that object's GetClosestPointOn method.

To do this, get the [IFace2](#), [IEdge](#), or [IVertex](#) object using the [ISelectionMgr::GetSelectedObject6](#) method, and then use that object to call GetClosestPointOn. Pass the X,Y,Z values returned from ISelectionMgr::GetSelectionPoint2 or ISelectionMgr::IGetSelectionPoint2, and the GetClosestPointOn method will return the closest X,Y,Z point that is on the face, edge, or vertex.

If the selected object is sketch geometry, then the coordinates returned are in sketch space. The coordinates are 2D and related to the origin of the sketch that owns the selected geometry.

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)

[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::SetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectionPointInSketchSpace Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectionPointInSketchSpace Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectionPointInSketchSpace2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectionPointInSketchSpace( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object
```

```
value = instance.GetSelectionPointInSketchSpace(AtIndex)
```

C#

```
System.object GetSelectionPointInSketchSpace(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ GetSelectionPointInSketchSpace(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectionPointInSketchSpace](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectionPointInSketchSpace2 Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectionPointInSketchSpace2 Method (ISelectionMgr)

Gets the selection point projected on to the active sketch and returned in sketch space.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectionPointInSketchSpace2( _  
    ByVal Index As System.Integer, _  
    ByVal Mark As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim Index As System.Integer  
Dim Mark As System.Integer  
Dim value As System.Object  
  
value = instance.GetSelectionPointInSketchSpace2(Index, Mark)
```

C#

```
System.object GetSelectionPointInSketchSpace2(  
    System.int Index,  
    System.int Mark  
)
```

C++/CLI

```
System.Object^ GetSelectionPointInSketchSpace2(  
& System.int Index,  
& System.int Mark  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index position with in the current list of selected items, where AtIndex ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**).

Mark

- 1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value that was used to mark and select an object

Return Value

Array of 3 doubles (x,y,z)

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectionPointInSketchSpace2](#).

Example

[Create Line From User Selection \(VBA\)](#)

Remarks

The selection point is projected on to the currently active sketch, resulting in a z value of 0.00.

If a sketch is not currently active, then the return value is the same as that returned by [ISelectionMgr::GetSelectionPoint2](#) or [ISelectionMgr::!GetSelectionPoint2](#). You can determine if a sketch is active by checking for a Nothing or null return value from [IModelDoc2::GetActiveSketch2](#) or [IModelDoc2::!GetActiveSketch2](#).

The index starts at 1. However, if you specify -1 for the Index argument, then the Mark argument is ignored and the dynamically highlighted view is selected if dynamic highlighting is turned on. See also IAssemblyDoc event [DynamicHighlightNotify](#), IDrawingDoc event [DynamicHighlightNotify](#), and IPartDoc event [DynamicHighlightNotify](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::!GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::GetSelectedObjectCount2 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)

[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::IDeSelect2 Method](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::GetSelectByIdSpecification Method](#)
[ISelectionMgr::GetSelectionSpecification Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectionSpecification Method (ISelectionMgr)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : GetSelectionSpecification Method (ISelectionMgr)

Gets the selection specification at the specified index of the current selection list.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectionSpecification( _  
    ByVal Index As System.Integer, _  
    ByRef SelectByString As System.String, _  
    ByRef ObjectType As System.String, _  
    ByRef Type As System.Integer, _  
    ByRef X As System.Double, _  
    ByRef Y As System.Double, _  
    ByRef Z As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim Index As System.Integer  
Dim SelectByString As System.String  
Dim ObjectType As System.String  
Dim Type As System.Integer  
Dim X As System.Double  
Dim Y As System.Double  
Dim Z As System.Double  
Dim value As System.Boolean
```

```
value = instance.GetSelectionSpecification(Index, SelectByString, ObjectType, Type, X, Y, Z)
```

C#

```
System.bool GetSelectionSpecification(  
    System.int Index,  
    out System.string SelectByString,  
    out System.string ObjectType,  
    out System.int Type,  
    out System.double X,  
    out System.double Y,  
    out System.double Z  
)
```

C++/CLI

```
System.bool GetSelectionSpecification(  
& System.int Index,  
& [Out] System.String^ SelectByString,  
& [Out] System.String^ ObjectType,  
& [Out] System.int Type,  
& [Out] System.double X,  
& [Out] System.double Y,  
& [Out] System.double Z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

1 <= Index in the current list of selected items <= [ISelectionMgr::GetSelectedObjectCount2](#)

SelectByString

Feature name of object at Index; "" if object is not a feature

ObjectType

Type of object at Index

Type

Type of object at Index as defined in [swSelectType_e](#)

X

X coordinate of object at Index; 0 if SelectByString is not ""

Y

Y coordinate of object at Index; 0 if SelectByString is not ""

Z

Z coordinate of object at Index; 0 if SelectByString is not ""

Return Value

True if successful, false if not

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::GetSelectionSpecification](#).

Example

[Get Selection Specification \(VBA\)](#)

[Get Selection Specification \(VB.NET\)](#)

[Get Selection Specification \(C#\)](#)

See Also

[ISelectionMgr Interface](#)

[ISelectionMgr Members](#)

[ISelectionMgr::GetSelectByIdSpecification Method \(\)](#)

[ISelectionMgr::GetSelectedObject6 Method \(\)](#)

[IModelDocExtension::SelectById2 Method \(\)](#)

[IFeature::GetNameForSelection Method \(\)](#)

[ISelectionMgr::GetSelectedObjectLoop2 Method \(\)](#)

[ISelectionMgr::GetSelectedObjectMark Method \(\)](#)

[ISelectionMgr::GetSelectedObjectsComponent4 Method \(\)](#)

[ISelectionMgr::GetSelectedObjectsDrawingView2 Method \(\)](#)

[ISelectionMgr::GetSelectedObjectType3 Method \(\)](#)

[ISelectionMgr::GetSelectionPoint2 Method \(\)](#)

[ISelectionMgr::GetSelectionPointInSketchSpace2 Method \(\)](#)

[ISelectionMgr::SetSelectedObjectMark Method \(\)](#)

[ISelectionMgr::SetSelectionPoint2 Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

IDeSelect Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : IDeSelect Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::IDeSelect2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IDeSelect( _  
    ByVal Count As System.Integer, _  
    ByRef AtIndex As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim Count As System.Integer  
Dim AtIndex As System.Integer  
Dim value As System.Integer
```

```
value = instance.IDeSelect(Count, AtIndex)
```

C#

```
System.int IDeSelect(  
    System.int Count,  
    ref System.int AtIndex  
)
```

C++/CLI

```
System.int IDeSelect(  
& System.int Count,  
& System.int% AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr.IDeSelect](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IDeSelect2 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : IDeSelect2 Method (ISelectionMgr)

Deselects the specified entity.

.NET Syntax

Visual Basic (Declaration)

```
Function IDeSelect2(  
    ByVal Count As System.Integer, _  
    ByRef AtIndex As System.Integer, _  
    ByVal Mark As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)

```
Dim instance As ISelectionMgr  
Dim Count As System.Integer  
Dim AtIndex As System.Integer  
Dim Mark As System.Integer  
Dim value As System.Integer
```

```
value = instance.IDeSelect2(Count, AtIndex, Mark)
```

C#

```
System.int IDeSelect2(  
    System.int Count,  
    ref System.int AtIndex,  
    System.int Mark  
)
```

C++/CLI



```
System.int IDeSelect2(  
& System.int Count,  
& System.int% AtIndex,  
& System.int Mark  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of objects to deselect

AtIndex

Index position within the current list of selected items where index ranges from 1 to [ISelectionMgr::GetSelectedObjectCount2](#) (see **Remarks**)

Mark

- -1 = All selections regardless of marks
- 0 = only the selections without marks
- Any other value = Value that was used to mark and select an object

Return Value

1 if the specified entity is deselected, 0 if not

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::IDeSelect2](#).

Remarks

AtIndex should be either an array of 32-bit integers or a single 32-bit integer. See [Long vs. Integer](#) for details about data types.

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)
[ISelectionMgr::DeSelect2 Method](#)
[ISelectionMgr::GetSelectedObject6 Method](#)
[ISelectionMgr::GetSelectedObjectCount2 Method](#)
[ISelectionMgr::GetSelectedObjectLoop2 Method](#)
[ISelectionMgr::GetSelectedObjectMark Method](#)
[ISelectionMgr::GetSelectedObjectsComponent3 Method](#)
[ISelectionMgr::GetSelectedObjectsDrawingView2 Method](#)
[ISelectionMgr::GetSelectedObjectType3 Method](#)
[ISelectionMgr::GetSelectionPoint2 Method](#)
[ISelectionMgr::GetSelectionPointInSketchSpace2 Method](#)
[ISelectionMgr::IGetSelectionPoint2 Method](#)
[ISelectionMgr::IGetSelectionPointInSketchSpace2 Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetSelectedObject Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : IGetSelectedObject Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetSelectedObject( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object
```



```
value = instance.IGetSelectedObject(AtIndex)
```

C#

```
System.object IGetSelectedObject(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ IGetSelectedObject(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::IGetSelectedObject](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetSelectedObject2 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : IGetSelectedObject2 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetSelectedObject2( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object
```

```
value = instance.IGetSelectedObject2(AtIndex)
```

C#

```
System.object IGetSelectedObject2(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ IGetSelectedObject2(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::IGetSelectedObject2](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetSelectedObject3 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : IGetSelectedObject3 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetSelectedObject3( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.IGetSelectedObject3(AtIndex)
```

C#

```
System.object IGetSelectedObject3(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ IGetSelectedObject3(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::IGetSelectedObject3](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetSelectedObject4 Method (ISelectionMgr)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISelectionMgr Interface](#) : IGetSelectedObject4 Method (ISelectionMgr)

Obsolete. Superseded by [ISelectionMgr::GetSelectedObject6](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IGetSelectedObject4( _  
    ByVal AtIndex As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISelectionMgr  
Dim AtIndex As System.Integer  
Dim value As System.Object  
  
value = instance.IGetSelectedObject4(AtIndex)
```

C#

```
System.object IGetSelectedObject4(  
    System.int AtIndex  
)
```

C++/CLI

```
System.Object^ IGetSelectedObject4(  
& System.int AtIndex  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AtIndex

Visual Basic for Applications (VBA) Syntax

See [SelectionMgr::IGetSelectedObject4](#).

See Also

[ISelectionMgr Interface](#)
[ISelectionMgr Members](#)