

SOLIDWORKS Document Manager API (.NET) — Reference (16/19): ISwDMDocument7- ISwDMSheet4

SOLIDWORKS API Documentation (converted from CHM)

ISwDMDocument7 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument7 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument7 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDocument7
    Inherits ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument7
```

C#

```
public interface ISwDMDocument7 :
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6
```

C++/CLI

```
public interface class ISwDMDocument7 : public
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument7](#).

Remarks

Before you can access this object, you must call [ISwDMAApplication::GetDocument](#).

NOTES:

- You can access an ISwDMDocument7 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to an ISwDMDocument7 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMAApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument7 Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)

[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument7 Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument7 Interface

For a list of all members of this type, see [ISwDMDocument7 members](#).

Public Methods

Name	Description
 IsSmartComponentDocument	Gets whether this document is a smart component.

[Top](#)

See Also

[ISwDMDocument7 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument7 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument7 Interface

The following tables list the members exposed by [ISwDMDocument7](#).

Public Methods

Name	Description
 IsSmartComponentDocument	Gets whether this document is a smart component.

[Top](#)

See Also

[ISwDMDocument7 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument8 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)

[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

IsSmartComponentDocument Method (ISwDMDocument7)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument7 Interface](#) : IsSmartComponentDocument Method (ISwDMDocument7)

Gets whether this document is a smart component.

.NET Syntax

Visual Basic (Declaration)

```
Function IsSmartComponentDocument() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument7  
Dim value As System.Boolean
```

```
value = instance.IsSmartComponentDocument()
```

C#

```
System.bool IsSmartComponentDocument()
```

C++/CLI

```
System.bool IsSmartComponentDocument();
```

Return Value

True if the document is a smart component, false if not

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument7::IsSmartComponentDocument](#).

See Also

[ISwDMDocument7 Interface](#)
[ISwDMDocument7 Members](#)

Availability

SOLIDWORKS Document Manager API 2007 FCS

ISwDMDocument8 (Type)

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

ISwDMDocument8 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMDocument8 Interface

Accesses the document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMDocument8
    Inherits
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument8
```

C#

```
public interface ISwDMDocument8 :
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7
```

C++/CLI

```
public interface class ISwDMDocument8 : public
    ISwDMDocument, ISwDMDocument3, ISwDMDocument4, ISwDMDocument5, ISwDMDocument6, ISwDMDocument7
```

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument8](#).

Remarks

Before you can access this object, you must call [ISwDMAApplication::GetDocument](#).

NOTES:

- You can access an SwDMDocument8 object by calling QueryInterface on an [ISwDMDocument](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMDocument object can be assigned to a SwDMDocument8 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMAApplication::GetDocument](#)

[ISwDMConfiguration::Document](#)

[ISwDMConfigurationMgr::Document](#)

See Also

[ISwDMDocument8 Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)

[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument8 Interface Members

[See Also](#) [Methods](#)

 [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument8 Interface

The following tables list the members exposed by [ISwDMDocument8](#).

Public Methods

Name	Description
 GetChangedReferences	Gets a list of the names of the original references and their corresponding new references if the references were changed using the SOLIDWORKS Document Manager API or SOLIDWORKS Explorer.
 GetComponentCount	Gets the number of components in a SOLIDWORKS assembly document.

[Top](#)

See Also

[ISwDMDocument8 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)
[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

ISwDMDocument8 Interface Methods

[See Also](#)

 [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMDocument8 Interface

For a list of all members of this type, see [ISwDMDocument8 members](#).

Public Methods

Name	Description
 GetChangedReferences	Gets a list of the names of the original references and their corresponding new references if the references were changed using the SOLIDWORKS Document Manager API or SOLIDWORKS Explorer.
 GetComponentCount	Gets the number of components in a SOLIDWORKS assembly document.

[Top](#)

See Also

[ISwDMDocument8 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument3 Interface](#)
[ISwDMDocument4 Interface](#)
[ISwDMDocument5 Interface](#)
[ISwDMDocument6 Interface](#)
[ISwDMDocument7 Interface](#)
[ISwDMDocument10 Interface](#)
[ISwDMDocument13 Interface](#)

[ISwDMDocument14 Interface](#)
[ISwDMDocument15 Interface](#)
[ISwDMDocument16 Interface](#)
[ISwDMDocument17 Interface](#)
[ISwDMDocument18 Interface](#)
[ISwDMDocument19 Interface](#)
[ISwDMDocument20 Interface](#)
[ISwDMDocument21 Interface](#)
[ISwDMDocument22 Interface](#)
[ISwDMDocument23 Interface](#)
[ISwDMDocument24 Interface](#)
[ISwDMDocument25 Interface](#)
[ISwDMDocument26 Interface](#)
[ISwDMDocument27 Interface](#)
[ISwDMDocument28 Interface](#)
[ISwDMDocument29 Interface](#)
[ISwDMDocument30 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetChangedReferences Method (ISwDMDocument8)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument8 Interface](#) : GetChangedReferences Method (ISwDMDocument8)

Gets a list of the names of the original references and their corresponding new references if the references were changed using the SOLIDWORKS Document Manager API or SOLIDWORKS Explorer.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetChangedReferences( _  
    ByRef originalreferences As System.Object, _  
    ByRef newreferences As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument8  
Dim originalreferences As System.Object  
Dim newreferences As System.Object  
  
instance.GetChangedReferences(originalreferences, newreferences)
```

C#

```
void GetChangedReferences(  
    out System.object originalreferences,  
    out System.object newreferences  
)
```

C++/CLI

```
void GetChangedReferences(  
& [Out] System.Object^ originalreferences,  
& [Out] System.Object^ newreferences  
)
```

Parameters

originalreferences

Array of the names of the original references

newreferences

Array of the names of the corresponding references

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument8::GetChangedReferences](#).

See Also

[ISwDMDocument8 Interface](#)
[ISwDMDocument8 Members](#)
[ISwDMDocument::ReplaceReference Method](#)
[ISwDMDocument5::GetAllExternalReferences2 Method](#)
[ISwDMConfiguration11::GetReplacedComponents Method](#)
[ISwDMDocument30::ClearChangedReferences Method \(\)](#)

Availability

SOLIDWORKS Document Manager API 2007 FCS

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetComponentCount Method (ISwDMDocument8)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMDocument8 Interface](#) : GetComponentCount Method (ISwDMDocument8)

Gets the number of components in a SOLIDWORKS assembly document.

.NET Syntax

Visual Basic (Declaration)

```
Function GetComponentCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMDocument8  
Dim value As System.Integer  
  
value = instance.GetComponentCount()
```

C#

```
System.int GetComponentCount()
```

C++/CLI

```
System.int GetComponentCount();
```

Return Value

Number of components in an assembly document

Visual Basic for Applications (VBA) Syntax

See [SwDMDocument8::GetComponentCount](#).

Remarks

This method supports SOLIDWORKS assembly documents only. A -1 is returned for all other types of SOLIDWORKS documents.

See Also

[ISwDMDocument8 Interface](#)
[ISwDMDocument8 Members](#)

Availability

SOLIDWORKS Document Manager API 2007 FCS

ISwDMExternalReferenceOption (Type)

ISwDMExternalReferenceOption Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMExternalReferenceOption Interface

Allows you to access information about external references from a document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMExternalReferenceOption

Visual Basic (Usage)



Dim instance As [ISwDMExternalReferenceOption](#)

C#

public interface ISwDMExternalReferenceOption

C++/CLI

public interface class ISwDMExternalReferenceOption

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption](#).

Accessors

[ISwDMAApplication4::GetExternalReferenceOptionObject2](#)

See Also

[ISwDMExternalReferenceOption Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMExternalReferenceOption2 Interface](#)
[ISwDMDocument18::GetExternalFeatureReferences2](#)

ISwDMExternalReferenceOption Interface Members

[See Also](#) [Properties](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMExternalReferenceOption Interface

The following tables list the members exposed by [ISwDMExternalReferenceOption](#).

Public Properties

Name	Description
 Configuration	Gets and sets the configuration from which to retrieve the information about the document's external references.
 ExternalReferences	Gets the names of the external references stored in the document.
 NeedSuppress	Gets and sets whether to retrieve information about suppressed external references in the document.
 ReferencedConfigurations	Gets the names of the configurations in the external references in the document.
 SearchOption	Gets and sets the search options for retrieving information about the external references in the document.

[Top](#)

See Also

ISwDMExternalReferenceOption Interface Properties

[See Also](#)

[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMExternalReferenceOption Interface

For a list of all members of this type, see [ISwDMExternalReferenceOption members](#).

Public Properties

Name	Description
 Configuration	Gets and sets the configuration from which to retrieve the information about the document's external references.
 ExternalReferences	Gets the names of the external references stored in the document.
 NeedSuppress	Gets and sets whether to retrieve information about suppressed external references in the document.
 ReferencedConfigurations	Gets the names of the configurations in the external references in the document.
 SearchOption	Gets and sets the search options for retrieving information about the external references in the document.

[Top](#)

See Also

[ISwDMExternalReferenceOption Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMExternalReferenceOption2 Interface](#)
[ISwDMDocument18::GetExternalFeatureReferences2](#)

Configuration Property (ISwDMExternalReferenceOption)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMExternalReferenceOption Interface](#) : Configuration Property (ISwDMExternalReferenceOption)

Gets and sets the configuration from which to retrieve the information about the document's external references.

.NET Syntax

Visual Basic (Declaration)

Property Configuration As System.String

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption  
Dim value As System.String
```

```
instance.Configuration = value
```

```
value = instance.Configuration
```

C#

```
System.string Configuration {get; set;}
```

C++/CLI

```
property System.String^ Configuration {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

Property Value

Name of the configuration

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption::Configuration](#).

Example

[Get External References \(C#\)](#)
[Get External References \(VB.NET\)](#)
[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(C#\)](#)
[Get Current Name of Configuration of Suppressed Component \(VB.NET\)](#)

See Also

[ISwDMExternalReferenceOption Interface](#)
[ISwDMExternalReferenceOption Members](#)
[ISwDMDocument15::GetExternalFeatureReferences Method](#)

Availability

SOLIDWORKS Document Manager API 2011 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ExternalReferences Property (ISwDMExternalReferenceOption)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMExternalReferenceOption Interface](#) : ExternalReferences Property (ISwDMExternalReferenceOption)

Gets the names of the external references stored in the document.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property ExternalReferences As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption  
Dim value As System.Object  
  
value = instance.ExternalReferences
```

C#

```
System.object ExternalReferences {get;}
```

C++/CLI

```
property System.Object^ ExternalReferences {  
    System.Object^ get();  
}
```

Property Value

An array of strings of the names of the external references

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption::ExternalReferences](#).

Example

[Get External References \(C#\)](#)
[Get External References \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(C#\)](#)
[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)

See Also

[ISwDMExternalReferenceOption Interface](#)
[ISwDMExternalReferenceOption Members](#)
[ISwDMDocument15::GetExternalFeatureReferences Method](#)

Availability

SOLIDWORKS Document Manager API 2011 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

NeedSuppress Property (ISwDMExternalReferenceOption)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMExternalReferenceOption Interface](#) : NeedSuppress Property (ISwDMExternalReferenceOption)

Gets and sets whether to retrieve information about suppressed external references in the document.

.NET Syntax

Visual Basic (Declaration)

```
Property NeedSuppress As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption  
Dim value As System.Boolean
```

```
instance.NeedSuppress = value
```

```
value = instance.NeedSuppress
```

C#

```
System.bool NeedSuppress {get; set;}
```

C++/CLI

```
property System.bool NeedSuppress {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

Property Value

True to retrieve suppressed references, false to not

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption::NeedSuppress](#).

Example

[Get External References \(VB.NET\)](#)
[Get External References \(C#\)](#)
[Get Current Name of Configuration of Suppressed Component \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(C#\)](#)
[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)

Remarks

To find out if a reference is suppressed:

1. Call [ISwDMComponent6::PathName](#) to set the component returned by [ISwDMDocument15::GetExternalFeatureReferences](#).
2. Call [ISwDMComponent::IsSuppressed](#).

The suppression states of all of the external references are also stored in the parent document. To obtain this information in XML format, call [ISwDMDocument::GetXMLStream](#).

See Also

[ISwDMExternalReferenceOption Interface](#)
[ISwDMExternalReferenceOption Members](#)

Availability

SOLIDWORKS Document Manager API 2011 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ReferencedConfigurations Property (ISwDMExternalReferenceOption)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMExternalReferenceOption Interface](#) : ReferencedConfigurations Property (ISwDMExternalReferenceOption)

Gets the names of the configurations in the external references in the document.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property ReferencedConfigurations As System.Object

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption  
Dim value As System.Object
```

```
value = instance.ReferencedConfigurations
```

C#

```
System.Object ReferencedConfigurations {get;}
```

C++/CLI

```
property System.Object^ ReferencedConfigurations {  
    System.Object^ get();  
}
```

Property Value

Array of strings of the names of the configurations

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption::ReferencedConfigurations](#).

Example

[Get External References \(C#\)](#)
[Get External References \(VB.NET\)](#)
[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)

See Also

[ISwDMExternalReferenceOption Interface](#)
[ISwDMExternalReferenceOption Members](#)
[ISwDMDocument15::GetExternalFeatureReferences Method](#)

Availability

SOLIDWORKS Document Manager API 2011 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

SearchOption Property (ISwDMExternalReferenceOption)

[See Also](#) [Example](#)



Gets and sets the search options for retrieving information about the external references in the document.

.NET Syntax

Visual Basic (Declaration)

Property SearchOption As SwDMSearchOption

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption
Dim value As SwDMSearchOption

instance.SearchOption = value
value = instance.SearchOption
```

C#

```
SwDMSearchOption SearchOption {get; set;}
```

C++/CLI

```
property SwDMSearchOption^ SearchOption {
    SwDMSearchOption^ get();
    void set ( & SwDMSearchOption^ value);
}
```

Property Value

An [ISwDMSearchOption](#) object

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption::SearchOption](#).

Example

[Get External References \(C#\)](#)
[Get External References \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(C#\)](#)
[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)

Remarks

To set this property:

1. Call [ISwDMAApplication::GetSearchOptionObject](#).
2. Modify the returned ISwDMSearchOption object as needed.
3. Assign this property to the modified ISwDMSearchOption object.

See Also

[ISwDMExternalReferenceOption Interface](#)
[ISwDMExternalReferenceOption Members](#)
[ISwDMDocument15::GetExternalFeatureReferences Method](#)

Availability

SOLIDWORKS Document Manager API 2011 SP0

ISwDMExternalReferenceOption2 (Type)

ISwDMExternalReferenceOption2 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMExternalReferenceOption2 Interface

Allows you to access information about external references from a document.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMExternalReferenceOption2
    Inherits ISwDMExternalReferenceOption
```

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption2
```

C#

```
public interface ISwDMExternalReferenceOption2 : ISwDMExternalReferenceOption
```

C++/CLI

```
public interface class ISwDMExternalReferenceOption2 : public ISwDMExternalReferenceOption
```

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption2](#).

Example

[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(C#\)](#)
[Get Current Name of Configuration of Suppressed Component \(VB.NET\)](#)

Remarks

- You can access an SwDMExternalReferenceOption2 object by calling QueryInterface on an [ISwDMExternalReferenceOption](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMExternalReferenceOption object can be assigned to a SwDMExternalReferenceOption2 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMApplication4::GetExternalReferenceOptionObject2](#)

See Also

[ISwDMExternalReferenceOption2 Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument18::GetExternalFeatureReferences2 Method \(\)](#)

ISwDMExternalReferenceOption2 Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMExternalReferenceOption2 Interface

The following tables list the members exposed by [ISwDMExternalReferenceOption2](#).

Public Properties

Name	Description
 BrokenStatus	Gets whether the external references are broken in the document.
 IDs	Gets the IDs of the external references in a document.

[Top](#)

Public Methods

Name	Description
 ReferencedFeatures	Gets the names and types of reference features in the document.

[Top](#)

See Also

[ISwDMExternalReferenceOption2 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument18::GetExternalFeatureReferences2 Method \(\)](#)

SOLIDWORKS Document Manager API Help [Send comments on this topic.](#)

ISwDMExternalReferenceOption2 Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMExternalReferenceOption2 Interface

For a list of all members of this type, see [ISwDMExternalReferenceOption2 members](#).

Public Methods

Name	Description
 ReferencedFeatures	Gets the names and types of reference features in the document.

[Top](#)

See Also

[ISwDMExternalReferenceOption2 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument18::GetExternalFeatureReferences2 Method \(\)](#)

SOLIDWORKS Document Manager API Help [Send comments on this topic.](#)

ISwDMExternalReferenceOption2 Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMExternalReferenceOption2 Interface

For a list of all members of this type, see [ISwDMExternalReferenceOption2 members](#).

Public Properties

Name	Description
 BrokenStatus	Gets whether the external references are broken in the document.
 IDs	Gets the IDs of the external references in a document.

[Top](#)

See Also

[ISwDMExternalReferenceOption2 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMDocument18::GetExternalFeatureReferences2 Method \(\)](#)

SOLIDWORKS Document Manager API Help [Send comments on this topic.](#)

BrokenStatus Property (ISwDMExternalReferenceOption2)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMExternalReferenceOption2 Interface](#) : BrokenStatus Property (ISwDMExternalReferenceOption2)

Gets whether the external references are broken in the document.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property BrokenStatus As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption2  
Dim value As System.Object  
  
value = instance.BrokenStatus
```

C#

```
System.Object BrokenStatus {get;}
```

C++/CLI

```
property System.Object^ BrokenStatus {  
    System.Object^ get();  
}
```

Property Value

Array of integers of the statuses of the external references as defined in [swDmReferenceStatus](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption2::BrokenStatus](#).

Example

[Get External References for Part \(C#\)](#)

[Get External References for Part \(VB.NET\)](#)

Remarks

See Also

[ISwDMExternalReferenceOption2 Interface](#)

[ISwDMExternalReferenceOption2 Members](#)

Availability

SOLIDWORKS Document Manager API 2014 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

IDs Property (ISwDMExternalReferenceOption2)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMExternalReferenceOption2 Interface](#) : IDs Property (ISwDMExternalReferenceOption2)

Gets the IDs of the external references in a document.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property IDs As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMExternalReferenceOption2  
Dim value As System.Object
```

```
value = instance.IDs
```

C#

```
System.Object IDs {get;}
```

C++/CLI

```
property System.Object^ IDs {  
    System.Object^ get();  
}
```

Property Value

Array of integers of the IDs of the external references in a document

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption2::IDs](#).

Example

[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)

Remarks

See Also

[ISwDMExternalReferenceOption2 Interface](#)
[ISwDMExternalReferenceOption2 Members](#)

Availability

SOLIDWORKS Document Manager API 2014 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ReferencedFeatures Method (ISwDMExternalReferenceOption2)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMExternalReferenceOption2 Interface](#) : ReferencedFeatures Method (ISwDMExternalReferenceOption2)

Gets the names and types of reference features in the document.

.NET Syntax

Visual Basic (Declaration)

```
Function ReferencedFeatures( _  
    ByRef FeatureNames As System.Object, _  
    ByRef FeatureTypes As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As ISwDMExternalReferenceOption2  
Dim FeatureNames As System.Object  
Dim FeatureTypes As System.Object  
Dim value As System.Boolean
```

```
value = instance.ReferencedFeatures(FeatureNames, FeatureTypes)
```

C#



```
System.bool ReferencedFeatures(  
    out System.object FeatureNames,  
    out System.object FeatureTypes  
)
```

C++/CLI

```
System.bool ReferencedFeatures(  
& [Out] System.Object^ FeatureNames,  
& [Out] System.Object^ FeatureTypes  
)
```

Parameters

FeatureNames

Array of strings of the names of the referenced features

FeatureTypes

Array of strings of the types of referenced features

Return Value

True if the method successfully executes, false if the method fails to execute

Visual Basic for Applications (VBA) Syntax

See [SwDMExternalReferenceOption2::ReferencedFeatures](#).

Example

[Get External References for Part \(C#\)](#)

[Get External References for Part \(VB.NET\)](#)

See Also

[ISwDMExternalReferenceOption2 Interface](#)

[ISwDMExternalReferenceOption2 Members](#)

Availability

SOLIDWORKS Document Manager API 2014 SP0

ISwDMSearchOption (Type)

ISwDMSearchOption Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSearchOption Interface

Allows you to specify the types of references and paths to search.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

 .NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMSearchOption

Visual Basic (Usage)

Dim instance As [ISwDMSearchOption](#)

C#

public interface ISwDMSearchOption

C++/CLI

public interface class ISwDMSearchOption

 Visual Basic for Applications (VBA) Syntax

See [SwDMSearchOption](#).

 Example

[Get Current Name of Configuration of Suppressed Component \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(C#\)](#)

 Remarks

The search filters restrict the types of files returned. Any API that deals with file references needs a list of paths where it can search for files.

Every ISwDMSearchOption object is independent and is passed as a parameter. Because the DLL can be used by several applications at the same time; it cannot be global.

 Accessors

[ISwDMApplication::GetSearchOptionObject](#)
[ISwDMExternalReferenceOption::SearchOption](#)

 See Also

[ISwDMSearchOption Members](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

ISwDMSearchOption Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSearchOption Interface

The following tables list the members exposed by [ISwDMSearchOption](#).

 Public Properties

Name	Description
------	-------------



[SearchFilters](#)

Gets or sets the search filters.

[Top](#)

Public Methods

Name	Description
 AddSearchPath	Adds a new search path.
 ClearAllSearchPaths	Removes all search paths.
 GetAllSearchPaths	Gets a list of all search paths.
 RemoveSearchPath	Removes the specified search path.

[Top](#)

See Also

[ISwDMSearchOption Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSearchOption Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSearchOption Interface

For a list of all members of this type, see [ISwDMSearchOption members](#).

Public Methods

Name	Description
 AddSearchPath	Adds a new search path.
 ClearAllSearchPaths	Removes all search paths.
 GetAllSearchPaths	Gets a list of all search paths.
 RemoveSearchPath	Removes the specified search path.

[Top](#)

See Also

[ISwDMSearchOption Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSearchOption Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSearchOption Interface

For a list of all members of this type, see [ISwDMSearchOption members](#).

Public Properties

Name	Description
 SearchFilters	Gets or sets the search filters.

[Top](#)

See Also

[ISwDMSearchOption Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

AddSearchPath Method (ISwDMSearchOption)

[See Also](#)



Adds a new search path.

.NET Syntax

Visual Basic (Declaration)

```
Sub AddSearchPath( _  
    ByVal newPath As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As ISwDMSearchOption  
Dim newPath As System.String  
  
instance.AddSearchPath(newPath)
```

C#

```
void AddSearchPath(  
    System.string newPath  
)
```

C++/CLI

```
void AddSearchPath(  
    & System.String^ newPath  
)
```

Parameters

newPath
Search path; for example, C:\parts

Visual Basic for Applications (VBA) Syntax

See [SwDMSearchOption::AddSearchPath](#).

See Also

[ISwDMSearchOption Interface](#)
[ISwDMSearchOption Members](#)

Availability

SOLIDWORKS Document Manager API 2004 FCS

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ClearAllSearchPaths Method (ISwDMSearchOption)

[See Also](#)



Removes all search paths.

.NET Syntax

Visual Basic (Declaration)

```
Sub ClearAllSearchPaths()
```

Visual Basic (Usage)



```
Dim instance As ISwDMSearchOption  
  
instance.ClearAllSearchPaths()
```

C#

```
void ClearAllSearchPaths()
```

C++/CLI

```
void ClearAllSearchPaths();
```

Visual Basic for Applications (VBA) Syntax

See [SwDMSearchOption::ClearAllSearchPaths](#).

See Also

[ISwDMSearchOption Interface](#)
[ISwDMSearchOption Members](#)

Availability

SOLIDWORKS Document Manager API 2004 FCS

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetAllSearchPaths Method (ISwDMSearchOption)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSearchOption Interface](#) : GetAllSearchPaths Method (ISwDMSearchOption)

Gets a list of all search paths.

.NET Syntax

Visual Basic (Declaration)

```
Function GetAllSearchPaths() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMSearchOption  
Dim value As System.Object  
  
value = instance.GetAllSearchPaths()
```

C#

```
System.object GetAllSearchPaths()
```

C++/CLI

```
System.Object^ GetAllSearchPaths();
```

Return Value

Array of search paths

Visual Basic for Applications (VBA) Syntax

See [SwDMSearchOption::GetAllSearchPaths](#).

See Also

[ISwDMSearchOption Interface](#)
[ISwDMSearchOption Members](#)

Availability

SOLIDWORKS Document Manager API 2004 FCS

RemoveSearchPath Method (ISwDMSearchOption)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSearchOption Interface](#) : RemoveSearchPath Method (ISwDMSearchOption)

Removes the specified search path.

.NET Syntax

Visual Basic (Declaration)

```
Sub RemoveSearchPath( _  
    ByVal remPath As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As ISwDMSearchOption  
Dim remPath As System.String  
  
instance.RemoveSearchPath(remPath)
```

C#

```
void RemoveSearchPath(  
    System.string remPath  
)
```

C++/CLI

```
void RemoveSearchPath(  
& System.String^ remPath  
)
```

Parameters

remPath

Search path to remove; for example, C:\parts

Visual Basic for Applications (VBA) Syntax

See [SwDMSearchOption::RemoveSearchPath](#).

See Also

[ISwDMSearchOption Interface](#)
[ISwDMSearchOption Members](#)

Availability

SOLIDWORKS Document Manager API 2004 FCS

SearchFilters Property (ISwDMSearchOption)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSearchOption Interface](#) : SearchFilters Property (ISwDMSearchOption)

Gets or sets the search filters.

.NET Syntax

Visual Basic (Declaration)

```
Property SearchFilters As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMSearchOption  
Dim value As System.Integer
```

```
instance.SearchFilters = value
```

```
value = instance.SearchFilters
```

C#

```
System.int SearchFilters {get; set;}
```

C++/CLI

```
property System.int SearchFilters {  
    System.int get();  
    void set ( & System.int value);  
}
```

Property Value

Filter search as defined by [SwDMSearchFilters](#)

Visual Basic for Applications (VBA) Syntax

See [SwDMSearchOption::SearchFilters](#).

Example

[Get External References for Part \(C#\)](#)
[Get External References for Part \(VB.NET\)](#)
[Get Current Name of Configuration of Suppressed Component \(C#\)](#)
[Get Current Name of Configuration of Suppressed Component \(VB.NET\)](#)

See Also

[ISwDMSearchOption Interface](#)
[ISwDMSearchOption Members](#)

Availability

SOLIDWORKS Document Manager API 2004 FCS

ISwDMSheet (Type)

ISwDMSheet Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet Interface

Accesses the drawing sheet.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ISwDMSheet

Visual Basic (Usage)

Dim instance As [ISwDMSheet](#)

C#

public interface ISwDMSheet

C++/CLI

public interface class ISwDMSheet

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet](#).

Accessors

[ISwDMDocument10::GetSheets](#)

[ISwDMTable5::Sheet](#)

[ISwDMView::Sheet](#)

See Also

- [ISwDMSheet Members](#)
- [SolidWorks.Interop.swdocumentmgr Namespace](#)
- [ISwDMSheet2 Interface](#)
- [ISwDMSheet3 Interface](#)
- [ISwDMSheet4 Interface](#)

ISwDMSheet Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet Interface

The following tables list the members exposed by [ISwDMSheet](#).

Public Properties

Name	Description
Name	Gets the name of the drawing sheet.

[Top](#)

Public Methods

Name	Description
GetInvisibleCustomProperty	Gets the sheet's specified invisible sheet custom property.

 GetInvisibleCustomPropertyCount	Gets the number of invisible custom properties for this sheet.
 GetInvisibleCustomPropertyNames	Gets the names of this sheet's invisible custom properties.

[Top](#)

 See Also

[ISwDMSheet Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet3 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSheet Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet Interface

For a list of all members of this type, see [ISwDMSheet members](#).

 Public Methods

Name	Description
 GetInvisibleCustomProperty	Gets the sheet's specified invisible sheet custom property.
 GetInvisibleCustomPropertyCount	Gets the number of invisible custom properties for this sheet.
 GetInvisibleCustomPropertyNames	Gets the names of this sheet's invisible custom properties.

[Top](#)

 See Also

[ISwDMSheet Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet3 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSheet Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet Interface

For a list of all members of this type, see [ISwDMSheet members](#).

 Public Properties

Name	Description
 Name	Gets the name of the drawing sheet.

[Top](#)

 See Also

[ISwDMSheet Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet3 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetInvisibleCustomProperty Method (ISwDMSheet)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet Interface](#) : GetInvisibleCustomProperty Method (ISwDMSheet)

Gets the sheet's specified invisible sheet custom property.

 .NET Syntax

Visual Basic (Declaration)

```
Function GetInvisibleCustomProperty( _
    ByVal FieldName As System.String, _
    ByRef type As SwDmCustomInfoType _
) As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet
Dim FieldName As System.String
Dim type As SwDmCustomInfoType
Dim value As System.String

value = instance.GetInvisibleCustomProperty(FieldName, type)
```

C#

```
System.string GetInvisibleCustomProperty(
    System.string FieldName,
    out SwDmCustomInfoType type
)
```

C++/CLI

```
System.String^ GetInvisibleCustomProperty(
    & System.String^ FieldName,
    & [Out] SwDmCustomInfoType type
)
```

Parameters

FieldName
Name of the custom property
type
Type of custom property as defined by [swDmCustomInfoType](#)

Return Value

Value of the custom property

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet::GetInvisibleCustomProperty](#).

Remarks

Before calling this method, call [ISwDMSheet::GetInvisibleCustomPropertyNames](#).

See Also

[ISwDMSheet Interface](#)
[ISwDMSheet Members](#)
[ISwDMSheet::GetInvisibleCustomPropertyCount Method](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetInvisibleCustomPropertyCount Method (ISwDMSheet)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet Interface](#) : GetInvisibleCustomPropertyCount Method (ISwDMSheet)

Gets the number of invisible custom properties for this sheet.

.NET Syntax

Visual Basic (Declaration)

```
Function GetInvisibleCustomPropertyCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet
Dim value As System.Integer

value = instance.GetInvisibleCustomPropertyCount()
```

C#

```
System.int GetInvisibleCustomPropertyCount()
```

C++/CLI

```
System.int GetInvisibleCustomPropertyCount();
```

Return Value

Number of invisible custom properties

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet::GetInvisibleCustomPropertyCount](#).

See Also

[ISwDMSheet Interface](#)
[ISwDMSheet Members](#)
[ISwDMSheet::GetInvisibleCustomProperty Method](#)
[ISwDMSheet::GetInvisibleCustomPropertyNames Method](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetInvisibleCustomPropertyNames Method (ISwDMSheet)

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet Interface](#) : GetInvisibleCustomPropertyNames Method (ISwDMSheet)

Gets the names of this sheet's invisible custom properties.

.NET Syntax

Visual Basic (Declaration)

```
Function GetInvisibleCustomPropertyNames() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet
Dim value As System.Object

value = instance.GetInvisibleCustomPropertyNames()
```

C#

```
System.object GetInvisibleCustomPropertyNames()
```

C++/CLI

```
System.Object^ GetInvisibleCustomPropertyNames();
```

Return Value

Array of strings of the names of the invisible custom properties for this sheet

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet::GetInvisibleCustomPropertyNames](#).

Remarks

Before calling this method, call [ISwDMSheet::GetInvisibleCustomPropertyCount](#) to determine the size of the array.

Call this method before calling [ISwDMSheet::GetInvisibleCustomProperty](#) to determine the name of the invisible custom property you want to use with that method.

See Also

[ISwDMSheet Interface](#)
[ISwDMSheet Members](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

Name Property (ISwDMSheet)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet Interface](#) : Name Property (ISwDMSheet)

Gets the name of the drawing sheet.

.NET Syntax

Visual Basic (Declaration)

Property Name As System.String

Visual Basic (Usage)



```
Dim instance As ISwDMSheet  
Dim value As System.String
```

```
instance.Name = value
```

```
value = instance.Name
```

C#

```
System.string Name {get; set;}
```

C++/CLI

```
property System.String^ Name {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

Property Value

Name of drawing sheet.

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet::Name](#).

Example

[Get Preview Bitmaps of Drawing Sheets \(C#\)](#)
[Get Preview Bitmaps of Drawing Sheets \(VB.NET\)](#)

See Also

[ISwDMSheet Interface](#)
[ISwDMSheet Members](#)

Availability

SOLIDWORKS Document Manager API 2009 SP0

ISwDMSheet2 (Type)

ISwDMSheet2 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMSheet2 Interface

Accesses the drawing sheet.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMSheet2
    Inherits ISwDMSheet
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet2
```

C#

```
public interface ISwDMSheet2 : ISwDMSheet
```

C++/CLI

```
public interface class ISwDMSheet2 : public ISwDMSheet
```

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet2](#).

Example

[Get Preview Bitmaps of Drawing Sheets \(C#\)](#)
[Get Preview Bitmaps of Drawing Sheets \(VB.NET\)](#)

Remarks

- You can access an SwDMSheet2 object by calling QueryInterface on an [ISwDMSheet](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMSheet object can be assigned to a SwDMSheet2 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMDocument10::GetSheets](#)

[ISwDMTable5::Sheet](#)

[ISwDMView::Sheet](#)

See Also

[ISwDMSheet2 Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet3 Interface](#)
[ISwDMSheet4 Interface](#)

ISwDMSheet2 Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMSheet2 Interface

The following tables list the members exposed by [ISwDMSheet2](#).

Public Properties

Name	Description
 PreviewPNGStreamName	Gets the name of the stream for the preview bitmap (.png) of this sheet.

[Top](#)

Public Methods

Name	Description
 GetPreviewPNGBitmap	Gets the PNG preview bitmap (.png) for this sheet.
 GetPreviewPNGBitmapBytes	Gets the preview PNG byte array for this sheet.

[Top](#)

See Also

[ISwDMSheet2 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet3 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSheet2 Interface Methods

[See Also](#)

 [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet2 Interface

For a list of all members of this type, see [ISwDMSheet2 members](#).

Public Methods

Name	Description
 GetPreviewPNGBitmap	Gets the PNG preview bitmap (.png) for this sheet.
 GetPreviewPNGBitmapBytes	Gets the preview PNG byte array for this sheet.

[Top](#)

See Also

[ISwDMSheet2 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet3 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSheet2 Interface Properties

[See Also](#)

 [SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet2 Interface

For a list of all members of this type, see [ISwDMSheet2 members](#).

Public Properties

Name	Description
 PreviewPNGStreamName	Gets the name of the stream for the preview bitmap (.png) of this sheet.

[Top](#)

See Also

[ISwDMSheet2 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet3 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetPreviewPNGBitmap Method (ISwDMSheet2)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet2 Interface](#) : GetPreviewPNGBitmap Method (ISwDMSheet2)

Gets the PNG preview bitmap (.png) for this sheet.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPreviewPNGBitmap( _  
    ByRef result As SwDmPreviewError _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet2  
Dim result As SwDmPreviewError  
Dim value As System.Object
```

```
value = instance.GetPreviewPNGBitmap(result)
```

C#

```
System.object GetPreviewPNGBitmap(  
    out SwDmPreviewError result  
)
```

C++/CLI

```
System.Object^ GetPreviewPNGBitmap(  
& [Out] SwDmPreviewError result  
)
```

Parameters

result

Success or error code as defined by [swDmPreviewError](#)

Return Value

Pointer to the preview bitmap (.png) (an IPictureDisp*)

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet2::GetPreviewPNGBitmap](#).

Example

[Get Preview Bitmaps of Drawing Sheets \(C#\)](#)

[Get Preview Bitmaps of Drawing Sheets \(VB.NET\)](#)

Remarks

This method does not work in out-of-process and in ASP.NET/IIS web applications.

See Also

[ISwDMSheet2 Interface](#)

[ISwDMSheet2 Members](#)

[ISwDMSheet2::GetPreviewPNGBitmapBytes Method](#)

[ISwDMSheet2::PreviewPNGStreamName Property](#)

[ISwDMConfiguration7::GetPreviewPNGBitmap Method](#)

[ISwDMConfiguration9::GetPreviewPNGBitmapBytes Method](#)

[ISwDMConfiguration7::PreviewPNGStreamName Property](#)

[ISwDMDocument10::GetPreviewPNGBitmap Method](#)

[ISwDMDocument10::PreviewPNGStreamName Property](#)

[ISwDMDocument10::GetPreviewBitmap Method](#)

[ISwDMDocument10::PreviewStreamName Property](#)

Availability

SOLIDWORKS Document Manager API 2009 SP3

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetPreviewPNGBitmapBytes Method (ISwDMSheet2)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet2 Interface](#) : GetPreviewPNGBitmapBytes Method (ISwDMSheet2)

Gets the preview PNG byte array for this sheet.

Visual Basic Syntax

Visual Basic (Declaration)

```
Function GetPreviewPNGBitmapBytes( _  
    ByRef result As SwDmPreviewError _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet2  
Dim result As SwDmPreviewError  
Dim value As System.Object  
  
value = instance.GetPreviewPNGBitmapBytes(result)
```

C#

```
System.object GetPreviewPNGBitmapBytes(  
    out SwDmPreviewError result  
)
```

C++/CLI

```
System.Object^ GetPreviewPNGBitmapBytes(  
& [Out] SwDmPreviewError result  
)
```

Parameters

result

Success or error code as defined by [swDmPreviewError](#)

Return Value

Preview PNG byte array

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet2::GetPreviewPNGBitmap](#).

Example

[Get Preview Bitmaps of Drawing Sheets \(C#\)](#)
[Get Preview Bitmaps of Drawing Sheets \(VB.NET\)](#)

See Also

[ISwDMSheet2 Interface](#)
[ISwDMSheet2 Members](#)
[ISwDMSheet2::GetPreviewPNGBitmap Method](#)
[ISwDMSheet2::PreviewPNGStreamName Property](#)
[ISwDMSheet2::GetPreviewPNGBitmap Method](#)
[ISwDMDocument10::PreviewPNGStreamName Property](#)
[ISwDMDocument10::PreviewPNGStreamName Property](#)
[ISwDMConfiguration9::GetPreviewPNGBitmapBytes Method](#)
[ISwDMConfiguration7::GetPreviewPNGBitmap Method](#)
[ISwDMConfiguration7::PreviewPNGStreamName Property](#)
[ISwDMDocument10::PreviewStreamName Property](#)
[ISwDMDocument10::GetPreviewBitmap Method](#)

Availability

SOLIDWORKS Document Manager API 2009 SP3

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

PreviewPNGStreamName Property (ISwDMSheet2)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet2 Interface](#) : PreviewPNGStreamName Property (ISwDMSheet2)

Gets the name of the stream for the preview bitmap (.png) of this sheet.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property PreviewPNGStreamName As System.String
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet2  
Dim value As System.String  
  
value = instance.PreviewPNGStreamName
```

C#

```
System.string PreviewPNGStreamName {get;}
```

C++/CLI

```
property System.String^ PreviewPNGStreamName {  
    System.String^ get();  
}
```

Property Value

Name of the stream for the preview bitmap (.png) or an empty string if preview bitmap (.png) does not exist

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet2::PreviewPNGStreamName](#).

Example

[Get Preview Bitmaps of Drawing Sheet \(C#\)](#)
[Get Preview Bitmaps of Drawing Sheet \(VB.NET\)](#)

See Also

[ISwDMSheet2 Interface](#)
[ISwDMSheet2 Members](#)
[ISwDMSheet2::GetPreviewPNGBitmap Method](#)
[ISwDMSheet2::GetPreviewPNGBitmapBytes Method](#)
[ISwDMDocument10::GetPreviewPNGBitmap Method](#)
[ISwDMDocument10::PreviewPNGStreamName Property](#)
[ISwDMConfiguration9::GetPreviewPNGBitmapBytes Method](#)
[ISwDMConfiguration7::GetPreviewPNGBitmap Method](#)
[ISwDMConfiguration7::PreviewPNGStreamName Property](#)
[ISwDMDocument10::GetPreviewBitmap Method](#)
[ISwDMDocument10::PreviewStreamName Property](#)

Availability

SOLIDWORKS Document Manager API 2009 SP3

ISwDMSheet3 (Type)

ISwDMSheet3 Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet3 Interface

Accesses the drawing sheet.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMSheet3
    Inherits ISwDMSheet, ISwDMSheet2
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet3
```

C#

```
public interface ISwDMSheet3 : ISwDMSheet, ISwDMSheet2
```

C++/CLI

```
public interface class ISwDMSheet3 : public ISwDMSheet, ISwDMSheet2
```

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet3](#).

Remarks

- You can access an SwDMSheet3 object by calling QueryInterface on an [ISwDMSheet](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMSheet object can be assigned to a SwDMSheet3 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

- [ISwDMDocument10::GetSheets](#)
- [ISwDMTable5::Sheet](#)
- [ISwDMView::Sheet](#)

See Also

- [ISwDMSheet3 Members](#)
- [SolidWorks.Interop.swdocumentmgr Namespace](#)
- [ISwDMSheet Interface](#)
- [ISwDMSheet2 Interface](#)
- [ISwDMSheet4 Interface](#)

ISwDMSheet3 Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet3 Interface

The following tables list the members exposed by [ISwDMSheet3](#).

Public Methods

Name	Description
------	-------------



[GetID](#)

Gets the ID of the drawing sheet.

[Top](#)

See Also

[ISwDMSheet3 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSheet3 Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet3 Interface

For a list of all members of this type, see [ISwDMSheet3 members](#).

Public Methods

Name

Description



[GetID](#)

Gets the ID of the drawing sheet.

[Top](#)

See Also

[ISwDMSheet3 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet4 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

GetID Method (ISwDMSheet3)

[See Also](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) > [ISwDMSheet3 Interface](#) : GetID Method (ISwDMSheet3)

Gets the ID of the drawing sheet.

.NET Syntax

Visual Basic (Declaration)

```
Function GetID() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet3  
Dim value As System.Integer  
  
value = instance.GetID()
```

C#

```
System.int GetID()
```

C++/CLI

```
System.int GetID();
```

Return Value

ID of the drawing sheet

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet3::GetID](#).

Example

[Get Sheet IDs \(VB.NET\)](#)
[Get Sheet IDs \(C#\)](#)

See Also

[ISwDMSheet3 Interface](#)
[ISwDMSheet3 Members](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0

ISwDMSheet4 (Type)

ISwDMSheet4 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMSheet4 Interface

Accesses the drawing sheet.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISwDMSheet4
    Inherits ISwDMSheet, ISwDMSheet2, ISwDMSheet3
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet4
```

C#

```
public interface ISwDMSheet4 : ISwDMSheet, ISwDMSheet2, ISwDMSheet3
```

C++/CLI

```
public interface class ISwDMSheet4 : public ISwDMSheet, ISwDMSheet2, ISwDMSheet3
```

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet4](#).

Example

[Get BOM Tables \(VB.NET\)](#)
[Get BOM Tables \(C#\)](#)

Remarks

- You can access an SwDMSheet4 object by calling QueryInterface on an [ISwDMSheet](#) object in C++ or by direct assignment in Visual Basic.
- The SwDMSheet object can be assigned to a SwDMSheet4 variable, just like the SOLIDWORKS [IModelDoc2](#) object can be assigned to a SOLIDWORKS [IPartDoc](#) variable.

Accessors

[ISwDMDocument10::GetSheets](#)
[ISwDMTable5::Sheet](#)
[ISwDMView::Sheet](#)

See Also

[ISwDMSheet4 Members](#)
[SolidWorks.Interop.swdocumentmgr.Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet3 Interface](#)

ISwDMSheet4 Interface Methods

[See Also](#)



[SolidWorks.Interop.swdocumentmgr.Namespace](#) : ISwDMSheet4 Interface

For a list of all members of this type, see [ISwDMSheet4 members](#).

Public Methods

Name	Description
 GetViews	Gets the views owned by this sheet.

[Top](#)

See Also

[ISwDMSheet4 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet3 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSheet4 Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet4 Interface

The following tables list the members exposed by [ISwDMSheet4](#).

Public Properties

Name	Description
 CustomPropertyView	Gets the drawing view on which this sheet's custom properties reside.

[Top](#)

Public Methods

Name	Description
 GetViews	Gets the views owned by this sheet.

[Top](#)

See Also

[ISwDMSheet4 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet3 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

ISwDMSheet4 Interface Properties

[See Also](#)



[SolidWorks.Interop.swdocumentmgr Namespace](#) : ISwDMSheet4 Interface

For a list of all members of this type, see [ISwDMSheet4 members](#).

Public Properties

Name	Description
 CustomPropertyView	Gets the drawing view on which this sheet's custom properties reside.

[Top](#)

See Also

[ISwDMSheet4 Interface](#)
[SolidWorks.Interop.swdocumentmgr Namespace](#)
[ISwDMSheet Interface](#)
[ISwDMSheet2 Interface](#)
[ISwDMSheet3 Interface](#)

SOLIDWORKS Document Manager API Help

[Send comments on this topic.](#)

CustomPropertyView Property (ISwDMSheet4)

[See Also](#)



Gets the drawing view on which this sheet's custom properties reside.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property CustomPropertyView As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet4  
Dim value As System.Object  
  
value = instance.CustomPropertyView
```

C#

```
System.Object CustomPropertyView {get;}
```

C++/CLI

```
property System.Object^ CustomPropertyView {  
    System.Object^ get();  
}
```

Property Value

[ISwDMView](#); null if the sheet has no views

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet4::CustomPropertyView](#).

Example

See the [ISwDMSheet4](#) examples.

Remarks

This property works only with documents saved in SOLIDWORKS 2017 or later.

See Also

[ISwDMSheet4 Interface](#)
[ISwDMSheet4 Members](#)

Availability

SOLIDWORKS Document Manager API 2017 FCS

SOLIDWORKS Document Manager API Help

[Send comments](#) on this topic.

GetViews Method (ISwDMSheet4)

[See Also](#)



SolidWorks.Interop.swdocumentmgr Namespace > [ISwDMSheet4 Interface](#) : GetViews Method (ISwDMSheet4)

Gets the views owned by this sheet.

.NET Syntax

Visual Basic (Declaration)

```
Function GetViews() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISwDMSheet4  
Dim value As System.Object  
  
value = instance.GetViews()
```

C#

```
System.object GetViews()
```

C++/CLI

```
System.Object^ GetViews();
```

Return Value

Array of [ISwDMViews](#) owned by this sheet

Visual Basic for Applications (VBA) Syntax

See [SwDMSheet4::GetViews](#).

Example

See the [ISwDMSheet4](#) examples.

See Also

[ISwDMSheet4 Interface](#)
[ISwDMSheet4 Members](#)

Availability

SOLIDWORKS Document Manager API 2017 FCS