# Realistic Eye Movements

Version 2.1.5

# Quickstart for a character with existing presets:

You can also watch the Ouickstart video.

REM comes with presets for characters generated with Mixamo Fuse, <u>Autodesk Character Generator</u>, <u>MakeHuman</u>, <u>Character Creator 3</u>, <u>DAZ Studio</u> and <u>UMA</u>. If you have such a character:

Add the scripts LookTargetController and EyeAndHeadAnimator from the Scripts folder to your character. Click on the "Import" button and import the preset for your character. Done!

# **About Realistic Eye Movements**

Thanks for purchasing Realistic Eye Movements! I hope this asset helps you bring your characters to life. If you have any questions or suggestions, please drop me at line at tore.knabe@gmail.com!

For discussions of this asset, visit the **Unity forum thread**.

The web page for this asset is Unity Asset: Realistic Eye Movements.

Realistic Eye Movements (REM) can control your character's eyes, head and eyelid movements to make them look around, at the player, or at objects, in a lifelike way. You can use it with characters that have eyes rigged to a Mecanim humanoid bone rig or characters that just have two separate eye gameobjects. You can assign points of interest in the character's environment for the character to look at, or let them just look around idly, or let them automatically look at the player when the player comes into view or keeps staring at them.

The animations use data from published research papers. For more information, see my blog entry.

This asset only provides scripts to control animation, no meshes or shaders. For realistic looking eye meshes and shaders, I recommend Scruvystorm Studios' <u>RealEyes</u> asset or Tanuki Digital's <u>Eye Advanced</u> asset, there's also Ricardo's <u>Realistic Eye</u> asset or RRFreelance's <u>Eye Shader</u> asset. You can compare the three assets in the <u>webplayer demo</u>.

The asset only works correctly if the head is looking straight ahead with respect to the character transform when the scene starts. If your character's head is not looking straight in the editor (e.g. looking to the character's left), please rotate it to look straight.

## How to Use

There are two main scripts in the folder RealisticEyeMovements/Scripts:

## LookTargetController.cs

Chooses what to look at and when to switch look targets.

#### EyeAndHeadAnimator.cs

Controls the animation of eyes, head and eyelids for a given look target.


If you want more control over where and when to look you can modify LookTargetController.cs or replace it with your own script that calls functions from EyeAndHeadAnimator.cs. You probably don't need to modify EyeAndHeadAnimator.cs.

Drag the two scripts onto your character game object in the scene hierarchy. Then either import a preset or proceed with the Setup below.

# Setup

If your character was generated with Mixamo Fuse, Autodesk's Character Generator, MakeHuman, Character Creator 3, DAZ Studio or UMA, instead of manually configuring the eyes and eyelids as described below, you can just load the correct configuration for it by importing the corresponding preset: see the section **Presets** below.

If you have a character for which you don't have a preset yet, the first step is to configure it in the **Setup** foldout of the EyeAndHeadAnimator component:



## **Update Type**


For most scenarios, you can leave **Update Type** to **Late Update**. If your animator is set to *Animate Physics*, you should change this to **Fixed Update** so when REM rotates the head the physics is in line with the rest of the character. This setting will only work when the animator is indeed set to *Animate Physis*.

The setting **External** gives you more fine-grained control over when exactly the head and eye movements are updated: you call Update1() and Update2() yourself. Normally you don't need that, but in certain special cases like for example you use different FinalIK components such as LookAtIK, FullBodyBipedIK (fbbik) the order of updates is important: LookAtIK normally runs before fbbik, so if fbbik rotates the upper body because the hands grab something to the side, the head will no longer look in the desired direction, so you need to update the FinalIK components yourself. You want fbbik to rotate the upper body so the hand can reach their target, then to let REM figure out where the head should look, then LookAtIK should actually turn the head, then REM should rotate the eyes. For such a scenario, check this box and then each frame call the two functions Update1 and Update2 on the EyeAndHeadAnimator component (with the correct deltaTime as parameter). Make sure Update1 is called before FinalIK orients the head (because Update1 sets the head target), and call Update2 after FinalIK is done orienting the head, because Update2 moves the eyes. For example:

```
eyeAndHeadAnimator.Update1(Time.deltaTime);
lookAtIK.solver.Update();
eyeAndHeadAnimator.Update2(Time.deltaTime);
```

<u>Here</u> is a short script that can be added to a character and which does the correct order of updates for the above scenario.


## Eye Setup



Set Eye Control to either Mecanim eye bones or Selected Objects.

If you choose *Mecanim eye bones*, your character must have a Mecanim humanoid rig and an Animator component. If your Mecanim rig has the eye bones assigned correctly, the script will find and use them to animate the eyes. Choose this option if your character's eye meshes are controlled by Mecanim eye bones.

If you choose Mecanim eye bones and you get the error message "Eye bones not found", then maybe you have checked "Optimize Game Objects" in the import settings:



Make sure Optimize Game Objects is unchecked. Even if you expose bones for eyes and eyelids, the transforms for these bones will be read-only so REM cannot control them.

If you choose *Selected Objects*, you can select game objects that are your character's eyes in the character's object hierarchy to be controlled by the script. Drag each into its corresponding slot in the component:




To quickly select a character's head bone in order to get more easily to the eye objects, select

the character in the hierarchy and then in the menu choose "*Tools/Realistic Eye Movemets/Select Mecanim Head*", or press the shortcut Ctrl+Shift+H.


Moving the eye via eye mesh blendshapes is not supported.

## **Eyelids Setup**

Once you've finished Eye Control, the box **Eyelid control** appears. If your character has eyelids that can be controlled by bones or blendshapes, the REM can control them to add realism. If not, leave the box **Eyelid control** set to *None*. If your character does have eyelids, set it to either Bones or *Blendshapes*.



If you choose *Bones*, find the eyelid bones in your character's hierarchy and drag them into the corresponding slots. Each eyelid slot can take an array of bones. Most characters have just one bone per eyelid, but you can assign several bones per eyelid if your character has them.




The slots for the lower eyelids can be left empty if your character doesn't have lower eyelids to animate.

If you choose *Blendshapes* for eyelid control, you don't need to assign anything here.

# Saving Positions

The next step is to save the positions for looking straight, looking up, looking down, and, if you enabled eyelid control, for closed eyes. This will tell the scripts the limits of how far the eyes can look up and down and how to move the eyelids.

For the following steps I recommend locking the inspector tab of the GameObject that has the EyeAndHeadAnimator component with the little padlock symbol in the inspector pane's upper right:




First, make sure the character looks straight by rotating the eyes if necessary. If you set eye control to *Mecanim bones*, rotate the eye bones. If you set eye control to *Eye gameobjects*, rotate the gameobjects you assigned.




If you enabled eyelid control, set the eyelids to how you want them to be when the character looks straight with open eyes.


If you set eyelid control by bones, rotate or position the eyelids bones to the desired position. You can set **Eyelid bone mode** to only save the position, rotation, or both of the eyelid bones for the different poses.



If you set eyelid control to blendshapes, set the blendshape values of the respective SkinnedMeshRenderers such that the eyelids are right. When the eyes and eyelids are correct for looking straight with open eyes, press the **Save** button next to **Eyes open, looking straight**:



After that, more buttons will appear.



The **Eyes closed**, **looking straight** line will only appear if you enabled eyelid control.

For each line, set the corresponding eye and eyelid positions and press Save. The easiest way to do that is to use the convenience buttons that select either the eyes or the lower/upper eylid bones and then adjust the eyes/eyelids for the respective pose:

Select:	Eyes	Upper eyelids	Lower eyelids

For **Eyes closed, looking straight**, make sure the eyes are looking straight ahead again and close the eyelids by moving or rotating the upper lids down and the lower up, until they look right for a closed eyes position. This is usually easiest by first rotating both upper eyelids down until only part of the iris is visible on both sides:




Then rotate the lower eyelids up to close the eyes and press **Save** in the line **Eyes closed, looking straight**:



Now press **Load** in the line **Eyes open, looking straight** to open the eyes and make it easier to adjust the next poses.

For **Looking up**, rotate the eyes up as far as still looks good. This position will be saved as the maximum upward angle for the eyes. If you enabled eyelid control, adjust the eyelids for that position. In humans, when we look up, the upper eyelids move up a bit and the lower eyelids move up a bit as well, so the eyelids "follow" the eyes. This adds a lot to the realism of eye movement. Then press **Save** in the line **Looking up**.



## Reference picture:



Hint: If your eye bones or eye gameobjects are oriented such that it is difficult to let them look upwards because none of the rotation axes is perpendicular to "up", just rotate the whole character so his/her head is looking along the global z axis and set the rotation pivot control to *Global*:



Now you can easily rotate the eyes around the global horizontal axis. You can rotate your character back after you have saved all positions.

Do the corresponding saving for **Looking down**: rotate the eyes as far down as looks realistic, adjust eyelids (by rotating and/or moving them) if you enabled eyelid control, then press **Save**.



Reference picture:



After you saved all required positions, the component knows all it needs about how to animate the lids. Click **Load** next to **Eyes open, looking straight** to let your character look straight ahead.

Eyes open, looking straight	Save	Load
Eyes closed, looking straight	Save	Load
Looking up	Save	Load
Looking down	Save	Load

After completing the setup, you can adjust other parameters in the component.

Draw Sightlines In Editor		
Main weight		<b>●</b> 1
▶ Eyes		
▶ Eyelids		
▶ Head		
▶ Setup		
Export	Import	Import legacy (.dat)

Checking **Draw Sightlines In Editor** lets you see where the eyes are looking exactly during Play mode in the editor window.

**Main weight** is the main control for how much REM moves eyes, eyelids and the head: if set to zero, REM doesn't move anything at all. If set to 1, the more specific weights determine how much to move eyes, eyelids, and the head. Concretely, the total influence of REM on the eyes is

main weight \* eye weight

The eye weight slider is in the eyes foldout.

The total influence of REM on the eyelids is

main weight \* eye weight \* eyelids weight


The total influence of REM on the head is

main weight \* head weight

You can use main weight to fade REM in and out when you want to let a temporary animation take control of the character's eyes for example.

The other parameters are grouped into three foldouts: Eyes, Eyelids, and Head.

# **Eyes Foldout**



Eyes weight determines how much control REM has over moving the eyes, from 0 to 1.0 means

REM doesn't move the eyes and leaves them as they are (in default pose or controlled by animation etc.). 1 means REM fully controls the eye look direction.

The **Use Micro Saccades** checkbox determines whether the eyes do those little darts from time to time that human eyes usually do and that add to how lifelike the eyes seem.

The Use Macro Saccades checkbox determines whether the eyes do larger darts from time to time (similar to micro saccades, but less frequent and larger angles). Macro saccades are not used when the character is looking at the player's face or when you call the LookAtPoiDirectly function.

The default is to use both micro and macro saccades for most lifelike animation.

The **Max Eye Horiz Angle** value determines how much the eyes can rotate horizontally away from the nose (so for the left eye, the angle how far it can look to the left relative to the head).

The **Max Eye Horiz Angle Towards Nose** value determines how much the eyes can rotate horizontally towards the nose (so for the left eye, the angle to the right). For some models, it looks better if the angle *Max Eye Horiz Angle Towards Nose* is smaller than *Max Eye Horiz Angle*.

Reference image:



**Idle target horiz angle**: In Look Idly mode, the next look target is chosen within this number of angles horizontally relative to looking forward.

The **Cross Eye Correction** value determines how much to prevent the eyes from looking cross-eyed when fixating on an object close to the head. The default value should work fine for most setups, but if you find your character still looks cross-eyes for close objects, you can increase it.

**Saccade Speed** determines how quick the eyes move during a saccade. 1 is the most realistic, but 0.5 looks better on most characters.

Micro saccades/min looking idle determines the average number of micro saccades per minute when looking around idly.

Micro saccades/min looking at POI determines the average number of micro saccades per minute when looking at a specific thing. This is usually higher than when looking idly.

Macro saccades per minute determines the average number of macro saccades per minute.

# **Eyelids Foldout**

▼ Eyelids		
Eyelids weight	•	1
Min next blink time	3	
Max next blink time	15	
Blink speed	•	1
Eye widen or squint	•	0
Eyelids follow eyes vertically	✓	

**Eyelids weight** determines how much control REM has over moving the eyelids, from 0 to 1. 0 means REM doesn't move the eyelids and leaves them as they are (in default pose or controlled by animation etc.). 1 means REM fully controls the eyelid movement.

You can control the frequency of blinking by setting **Min Next Blink Time** and **Max Next Blink Time**. After a blink, the time until the next blink is a random number of seconds between min blink time and max blink time.


In general, women tend to blink a bit more than men: in one study men blinked 12 times a minute on average, women 19 times.

**Blink Speed** allows you to modify the blink speed. Keep it at 1 for the default blink speed.


The **Eye Widen Or Squint** value determines how much the eyes are widened (in suprise) or squinted. A value of 0 means no widening or squinting. A value greater than 0 means widening, a value less than 0 means squinting. Widening only works when eyelids are controlled by bones. Squinting works for both kinds of control of eyelids: bones or blendshapes.

The **Eyelids Follow Eyes Vertically** checkbox determines whether the eyelids follow the eye's vertical movement a bit by moving up when the eye moves up and down when the eye moves down. This adds to the realism, so by default it is enabled.

## **Head Foldout**




Set **Head Control** to how you want REM to control head movement:



#### **Head Control: AnimatorIK**


AnimatorIK uses Mecanim's OnAnimatorIK function to orient the head. Adjust **Head weight** and **Body weight** for your character. Mecanim's OnAnimatorIK seems to work best for some characters if **Head weight** is set to a lower value than 1, because otherwise the head "overshoots" when looking to the side.

If you use this option, make sure that your character's animator has the IK pass enabled:



#### **Head Control: Transform**

You can also choose **Transform** to control the head, which uses a custom algorithm.




You can assing a head, neck and spine objects (or bones). REM will orient the head (and neck if available, according to the neck weights) and use the spine as reference "forward orientation" for computing head angles. If your character is a Mecanim humanoid, you can leave these slots empty; REM will find appropriate bones on its own. If you don't like how OnAnimatorIK is orienting the head of your Humanoid character, choose **Transform** (and you can leave the slots for Head etc blank); it doesn't have issues like overshooting.

If you character is not humanoid, you have to assign the correct objects/bones for head and spine in the slots. This head gameobject will then be rotated to make the character's head look in the right direction. If you set this, please make sure the gameobject that has the EyeAndHeadAnimator component's forward direction is along the head and eyes' forward direction, so its forward direction is where the character is "looking" along. Also make sure the object has a parent gameobject.

If your character's head is not animated by the animator component, the head orientation might drift over time when using Head Control Transform; the head is still looking in the right direction, but its Up direction wanders. In that case, check **Reset head at frame start** to fix the issue.

## **Head Control: Head Target**

Choosing **Head Target** for **Head Control** lets REM keep updating the position of the assigned object in the scene.



Create an empty object in the scene and assign in to the *Head target* slot. You can then assign this object to another system as well that orients the head, for example an Animation Rigging setup on your character. REM will move this target and the other system will rotate the head to look at it.

#### **Head Control: Final IK**


If you have **Final IK** in your project and want to use that to rotate the head, add FinalIK's LookAtIK component to the character (and optionally a FullBodyBipedIK component if you need it) and set Head Control to **Final IK**. In addition, the symbol USE\_FINAL\_IK needs to be defined in the Project Settings for REM to be able to use FinalIK.

Open *Project Settings* and in the *Player* tab under *Other Settings*, add USE\_FINAL\_IK to *Scripting Define Symbols*.

For Unity 2019:



For Unity 2020:



You might want to set LookAtIK's Head Weight slider to 1, because REM already takes head limits into account and with a slider value of 1 the character will look directly at their targets.


## **Head Animation Type**



The default head animation type is HillHybrid, an experimental method to make the head rotation look more realistic. If you want, you can switch to the old SmoothDamping method instead.

The **Head weight** slider value determines how much the script controls the character's head movement when looking at targets. A value of 0 means the head is controlled by animation only.

Additional head tilt and Additional neck tilt angles let you adjust the head and neck after the head has been orientated to look at the target.



You can animate this/set it through code in case you want your character to roll their head to express curiosity or so.

The **Head Speed for Switching Target** value allows you to increase or decrease the head turn speed when switching the look target from one to another.

The **Head Speed for Following Target** value allows you to increase or decrease the speed with which the head tracks its current look target.

If **Use Head Jitter** is checked, the head will keep moving slightly when looking at a point, to make it look more natural and less like a stiff robot. You can control the parameters of the head jitter with **Head Jitter Frequency** and **Head Jitter Amplitude**.

The **Limit Head Angle** value determines how much to limit the head's left/right rotation. At zero, the character turns his or her head towards the point of interest, at larger values the head is kept straight ahead and only the eyes look at the target point.

## **Presets**

The **Export** and **Import** buttons let you save and load presets. Once you set up the component, you can export the settings to a file. Similar characters can then be quickly set up by just dragging the LookTargetController and EyeAndHeadAnimator components onto them and importing the saved file. For a preset to be applicable to a character, the character needs to have a compatible structure with respect to the eye bones/blendshapes etc. For example, if your setup uses eyelid bones, then the names of the eyelid bones must be the same in the character you saved the preset from and the one you want to apply it to.

There are already presets in the folder Presets for these type of characters: MakeHuman, Autodesk Character Generator, Mixamo Fuse, Character Creator 3, DAZ Studio and UMA. If your character is one of these types, just drag a LookTargetController and a EyeAndHeadAnimator component on him, import the appropriate file from RealisticEyeAnimations/Presets and it should work. If you don't use the default eye shapes but random or custom ones, you might have to adjust the settings.

If you are importing a Mixamo preset for a Mixamo Fuse character and get an error message, make sure the **eyelids** mesh object in the character is called "Eyelids"--some Mixamo characters name it differently and then the preset will not work.

# **Adding the Scripts at Runtime**

You can add the scripts at runtime (for example if you generate your characters at runtime) and load a preset to have their eyes animated correctly. Here is an example of how you could add the scripts at runtime. Copy the preset to a folder in your project called StreamingAssets (a folder with that name will have all its files included unmodified in the final build). Then, after you generated a character in your code (let's say you saved it in the GameObject variable newCharacterGameObject), use this code (except if you use Android or WebGL, see below):

```
EyeAndHeadAnimator eyeAndHeadAnimator =
newCharacterGameObject.AddComponent<EyeAndHeadAnimator>();
eyeAndHeadAnimator.ImportFromFile(Application.streamingAssetsPath +
"/mypreset.json");
LookTargetController lookTargetController =
newGO.AddComponent<LookTargetController>();
lookTargetController.Initialize();
```

If you are using **Android** or **WebGL**, the way the contents of the StreamingAssets folder is accessed is different. Instead of the above code, use this:

```
#if UNITY_EDITOR || UNITY_STANDALONE

EyeAndHeadAnimator eyeAndHeadAnimator =
    newCharacterGameObject.AddComponent<EyeAndHeadAnimator>();
    eyeAndHeadAnimator.ImportFromFile(Application.streamingAssetsPath +
        "/mypreset.json");
    LookTargetController lookTargetController =
        newCharacterGameObject.AddComponent<LookTargetController>();
    lookTargetController.Initialize();

#else

StartCoroutine(LoadPreset("mypreset.json"));

#endif
```

And in the same class, add this code:

#### For Android:

```
using System.Collections;
using System.IO;
IEnumerator LoadPreset(string presetFilename)
{
    string path = "jar:file://" + Application.dataPath + "!/assets/" +
    presetFilename;
    wWW loadPreset = new WWW(path);

yield return loadPreset;

string newPath = Application.persistentDataPath + "/" + presetFilename;
File.WriteAllBytes(newPath, loadPreset.bytes);
EyeAndHeadAnimator eyeAndHeadAnimator =
    newCharacterGameObject.AddComponent<EyeAndHeadAnimator>();
    eyeAndHeadAnimator.ImportFromFile(newPath);
LookTargetController lookTargetController =
    newCharacterGameObject.AddComponent<LookTargetController>();
lookTargetController.Initialize();
}
```

#### For WebGL:

# **Using UMA (Unity Multipurpose Avatar)**

If you use UMA, you need to add the components at runtime because the characters are generated at runtime. The previous section described how to do this. Just use the existing preset UMA.json from the preset folder. In the case of UMA, you might need to wait a frame after the character is generated for all the bones to be added before applying the scripts. Here's how you can do this: after generating the character, use this code:

```
StartCoroutine(AddREM(newCharacterGameObject));
```


Here is the function AddREM (it adds the components after one frame to make sure all bones have been added by UMA):

```
IEnumerator AddREM(GameObject newGO)
{
    yield return null;
    yield return null;

        EyeAndHeadAnimator eyeAndHeadAnimator =
    newGO.AddComponent<EyeAndHeadAnimator>();
        eyeAndHeadAnimator.ImportFromFile(Application.streamingAssetsPath +
"/UMA.json");

        LookTargetController lookTargetController =
    newGO.AddComponent<LookTargetController>();
        lookTargetController.Initialize();
}
```

# LookTargetController



# **Look Targets**

The **LookTargetController** component lets you control where your character is looking. By default, the character looks around idly in random directions (close to straight ahead), and sometimes at the player if the player is in view. If you have specific objects in the character's environment that you want the character to choose as look targets, drag them into the array **Points of Interest**. The character will look at a random object from that list for some time, then choose another object from the list to look at.

If the player is in the character's view, the slider value of Loot at Player Ratio determines how

often the character chooses the player as next target to look at: for example, a slider value of 0.1 means the character chooses a random direction or an object from the Points of Interest list 90% of the time, and the player as look target 10% of the time. To not have the character look at the player, set this to 0.

The slider **Stare Back Factor** determines how quickly the character looks back at the player if the characters sees the player keep staring at him or her (so how sensitive the character is to being stared at).

The slider **Notice Player Distance** determines what distance the player has to come nearer than for the character to start looking at him. A value of 0 means the player coming closer has no effect. A value of 2 means if the character hasn't noticed the player before and the player comes into view and is closer than 2 units, the character starts looking at the player.

If you set the slider **Personal Space Distance** to a value greater than zero and the player comes closer than this distance, the character looks away (avoiding the player in a "shy" way).

The time the character looks at a target before choosing another target is a random number of seconds between **Min Look Time** and **Max Look Time**.

**Third Person Player Eye Center:** Realistic Eye Movements uses the main camera as Player by default (for settings like Look at Player Ratio), so if you are developing a 3<sup>rd</sup> person game, where the main camera does not show the player's perspective, you need to tell EyeAndHeadAnimator where the player's eyes are. For this, you assign a transform that is always located between the player character's eyes to the **Third Person Player Eye Center** slot of the non-player character's EyeAndHeadAnimator component (the one who is supposed to look at the player). You can create an empty gameobject if necessary, position it between the player character's eyes and parent it to the player's head bone. Also make sure the transform's forward direction is the same as the player head's forward direction. *Note: Player Eye Center is the center of the player character eyes, not the eye center of the character which has the EyeAndHeadAnimator component that you are editing!* 

The checkbox **Keep Target Even When Lost** determines whether the character keeps trying to look at the target (by turning the head and eyes as much as possible) even when the target gets behind the character, so out of sight. If the checkbox is off, the character will stop tracking the target (and return to looking around idly or at another point of interest).

There are four events in LookTargetController that you can subscribe to:

OnStartLookingAtPlayer, OnStopLookingAtPlayer, OnPlayerEntersPersonalSpace, and OnLookAwayFromShyness. For example, you might make your character smile every time he or she looks at the player:

```
lookTargetController.OnStartLookingAtPlayer.AddListener(OnStartLookingAtMe);

void OnStartLookingAtMe() {
    if ( lookTargetController.IsPlayerLookingAtMe() )
        StartSmiling();
}
```

# **VR: Virtual Reality Headsets**

By default, the script uses the camera tagged MainCamera to determine the player's position. If you use Unity's VR support, the script uses that to find out where the player's left and right eyes are. When characters look at the player, they will cycle randomly among the left and right eye and the mouth as look target (the so called "social triangle" people use when looking at someone's face). You don't need to change anything for the script to work in a VR scene.

# **Script API**

You can call these functions on the LookTargetController component for more control (if possible, call them from your LateUpdate function, not your Update function):

#### LookTargetController.cs

LootTargetController has optional delegates you can set for more control:

- IsPlayerInViewDelegate
  - Used to determine whether the player is in view, and can be looked at. Register your own function here if you want some more custom logic, for example based on distance, raycasting to see whether there are occluding things in between etc.
- IsPlayerLookingAtMeDelegate
  - Used to determine whether that player is looking at the character (for example to decide whether to stare back). Register your own function here if you want some more custom logic, for example based on distance, raycasting to see whether there are occluding things in between etc.
- GetPOIsDelegate
  - Called every time the character is ready to look at a new thing. Returns the things that the character can choose from to look at. So instead of assigning a fixed list at start, you can update the points of interest whenever needed via this delegate. This is useful if there are changing/appearing/disappearing things in the environment that the character can look at. For example, in VR House Disco, every time the character is ready to look at a new target, this delegate returns the other dancers in front of the character as potential look targets to choose from.

You can set a delegate like this:

```
lookTargetController.GetPOIsDelegate = UpdatePOIs;
```

## And here is an example delegate function:

The whole code for this example is <u>here</u>, it's from <u>VR House Disco</u>. It lets the character look at other characters in view.

#### void Blink( )

Makes the character blink.

## void ClearLookTarget()

Clears the current look target and makes the character look straight ahead, until a new order is issued (so the character doesn't notice the player even when he should according to settings like Look At Player Ratio, for example).

#### bool IsLookingAtPlayer()

Returns whether the character is currently looking at the player.

## bool IsPlayerInView()

Returns whether the character can see the player (only checks viewing angles, doesn't check range or for visual obstacles in between character and player)

#### bool IsPlayerLookingAtMe()

Returns whether the character is seeing the player looking at the character.

```
void LookAtPlayer(float duration=-1, float headLatency=0.075f)
```

Looks at the player for duration seconds. To keep looking until a new command is given, set duration to -1. HeadLatency determines how much later the head starts moving than the eyes.

#### void LookAroundIdly()

Starts looking around in random directions (close to straight ahead) or at points of interest if the list Points of Interest has objects. This uses the component's settings like Look At Player Ratio etc., so under certain conditions the player will be noticed or avoided.

void **LookAtPoiDirectly**(Transform targetTransform, float duration=-1, float headLatency=0.075f

Looks at a specific transform for duration seconds. Keeps following the transform with the eyes if the transform moves. After the duration has passed, the character continues looking according to the component settings (like Look At Player Ratio etc.). To keep looking until a new command is given, set duration to -1. HeadLatency determines how much later the head starts moving than the eyes.

```
void LookAtPoiDirectly(Vector3 targetPoint, float duration=-1, float headLatency=0.075f)
```

Looks at a specific point for duration seconds. To keep looking until a new command is given, set duration to -1. HeadLatency determines how much later the head starts moving

	than the eyes.
-	u need more control over the animation than the components can provide in their current state, e let me know at tore.knabe@gmail.com.
Good	l luck with your projects!
	Tore Knabe