MiniFlow Architecture

Let's consider how to implement this graph structure in MiniFlow. We'll use a Python class to represent a generic node.

```
class Node(object):
    def __init__(self):
        # Properties will go here!
```

We know that each node might receive input from multiple other nodes. We also know that each node creates a single output, which will likely be passed to other nodes. Let's add two lists: one to store references to the inbound nodes, and the other to store references to the outbound nodes.

Each node will eventually calculate a value that represents its output. Let's initialize the valueto Noneto indicate that it exists but hasn't been set yet.

Each node will need to be able to pass values forward and perform backpropagation (more on that later). For now, let's add a placeholder method for forward propagation. We'll deal with backpropagation later on.

```
class Node(object):
   def __init__(self, inbound_nodes=[]):
        # Node(s) from which this Node receives values
        self.inbound_nodes = inbound_nodes
        # Node(s) to which this Node passes values
        self.outbound_nodes = []
        # For each inbound Node here, add this Node as an outbound Node to _thu
        for n in self.inbound_nodes:
            n.outbound_nodes.append(self)
        # A calculated value
        self.value = None
   def forward(self):
        Forward propagation.
        Compute the output value based on `inbound_nodes` and
        store the result in self.value.
        raise NotImplemented
```

Nodes that Calculate

While Nodedefines the base set of properties that every node holds, only specialized subclasses of Nodewill end up in the graph. As part of this lab, you'll build the subclasses of Nodethat can perform calculations and hold values. For example, consider the Inputsubclass of Node.

```
class Input(Node):
    def __init__(self):
        # An Input node has no inbound nodes,
        # so no need to pass anything to the Node instantiator.
        Node.__init__(self)

# NOTE: Input node is the only node where the value
# may be passed as an argument to forward().
#
# All other node implementations should get the value
# of the previous node from self.inbound_nodes
```

```
#
# Example:
# val0 = self.inbound_nodes[0].value
def forward(self, value=None):
    # Overwrite the value if one is passed in.
    if value is not None:
        self.value = value
```

Unlike the other subclasses of Node, the Inputsubclass does not actually calculate anything. The Inputsubclass just holds a value, such as a data feature or a model parameter (weight/bias).

You can set **value**either explicitly or with the **forward()** method. This value is then fed through the rest of the neural network.

The Add Subclass

Add, which is another subclass of Node, actually can perform a calculation (addition).

```
class Add(Node):
    def __init__(self, x, y):
        Node.__init__(self, [x, y])

def forward(self):
    """

    You'll be writing code here in the next quiz!
    """
```

Notice the difference in the __init__method, Add.__init__(self, [x, y]). Unlike the Inputclass, which has no inbound nodes, the Addclass takes 2 inbound nodes, x and y, and adds the values of those nodes.