bitdispatcher manual

A free 911 computer-aided dispatch system in one program, set up entirely in the web interface: the dispatcher screen, the recorded map and aerial photos, road-routed recommendations, move-ups, the mobile terminal and reports built from the ledger.

88 chapters · 6 figures · 16 thousand words · BioDream LLC

Contents

1. **Part 1. Dispatching**
    1. Getting started
    2. Signing in: your duty, codes and the lock
    3. Call entry: the call-taker’s workspace
    4. Resources: approved guidance with the call
    5. The dispatcher screen
    6. Your own layout
    7. The full console
    8. Dispatching: reasons, warnings, plans and acknowledgement
    9. Screens on several monitors
    10. Incidents and call entry screen
    11. Fire houses screen
    12. Police status and mark-outs
    13. Unit status screen
    14. Map screen
    15. Incident and situation screen
    16. 911 calls
    17. Incidents
    18. Unit recommendations
    19. Advisory suggestions
    20. Move-up and cover
    21. Unit statuses
    22. The dispatch map
    23. Aerial photos
    24. Views: the place from every side
    25. Messages to and from the crews
    26. Alarms, plate readers and gunshot detection
    27. The station screen and toning out
    28. Incidents with neighbouring agencies
    29. Files and photos on an incident
    30. The command line
    31. Keyboard
2. **Part 2. In the field**
    32. Mobile data terminal
    33. Incident reports (RMS)
    34. NCIC inquiries

3. **Part 3. Supervising**
    35. The supervisor board
    36. Operations report
    37. The advisory codebook
    38. Ledger and audit
    39. Records and requests
    40. Disclosure rules

4. **Part 4. What 911 centres asked for**
    41. Transcripts and what was heard
    42. Callers in another language
    43. Where the caller is: device location and floor
    44. Many callers, one incident
    45. Non-emergency calls
    46. Vehicle crash data
    47. Drones
    48. Radio transcripts
    49. Incident summaries
    50. Critical calls and care
    51. Breaks and workload
    52. Training
    53. Exercises, injects and staging
    54. Quality review
    55. Working through an outage
    56. Line attacks (TDoS)
    57. Hooks and connections

5. **Part 5. Fire ground, crews and the police desk**
    58. Alarm levels: 2nd and 3rd alarms
    59. Personnel and crews
    60. Fire-ground accountability: roll calls (PAR)
    61. Paging responders
    62. Tow rotation
    63. Scheduled calls and special events
    64. Contacts directory and on-call lists
    65. Areas on the map (geofences)
    66. A unit's status history
    67. Patient-care reports (NEMSIS)
    68. Warrants and papers to serve
    69. Alerting the public
    70. Public alerts: settings and lists

6. **Part 6. Setting up**
    71. Units
    72. Stations
    73. Receiving facilities
    74. Call types and run cards
    75. Response plans
    76. Recording the map
    77. County GIS
    78. Settings
    79. Integrations
    80. BitVoice
    81. Users and positions
    82. Workstations
    83. Several sites
    84. Premises and hazards
    85. Migration from an earlier CAD
    86. Approved guidance
    87. Call-taking protocols
    88. This manual

PART 1

Dispatching

The dispatcher’s screen and everything done from it: calls, incidents, units, the map and the command line.

CHAPTER 1

Getting started

bitdispatcher is a computer-aided dispatch (CAD) system for 911 centres: one program with its own web interface. It creates and tracks incidents, recommends units by drive time over the road network, shows units, calls and incidents on a dispatch map with aerial photos, gives field crews a mobile terminal, and records every action in a tamper-evident ledger that reports are built from.




Figure 1. From a 911 call to a closed incident, and what each step writes to the ledger

The first hour

1. **Sign in** as the administrator with the password printed on first start, and choose **Administrator**. See Signing in (chapter 2).
2. **Record the map**: Admin › Map, choose the centre and radius, press Record. About two minutes for 100 miles. Open Map (chapter 76)
3. **Stations and units**: where units are based and what they are. Open Stations (chapter 72) Open Units (chapter 71)

4. **Call types and run cards**: what each kind of incident needs. The defaults are a sensible start. Open Call types (chapter 74)
5. **Users**: dispatchers, supervisors and field crews. Open Users (chapter 81)
6. **Call handling**: connect BitVoice, or point any call-handling system's ALI spill and EIDO at bitdispatcher. Open Integrations (chapter 79)

> bitdispatcher advises; the dispatcher decides. No feature dispatches a unit, closes an incident or changes a priority on its own.

Demo mode

Started with `-demo`, bitdispatcher seeds a fictional agency on the Roanoke, Virginia map (stations at real station positions, made-up units). With `bvsim`, a simulated BitVoice, calls ring and radios report positions; everything simulated is marked SIMULATED.

CHAPTER 2

Signing in: your duty, codes and the lock

Type your username and password. If you hold more than one duty, choose the one you are working: **Call-taker**, **Police**, **Fire** or **EMS dispatcher**, **Dispatcher (all disciplines)**, **Supervisor**, **Administrator** or **Records** (number keys choose). Your workspace opens for it, and what you may do follows it: the server enforces it, not only the screen.

Duty	Opens	May
Call-taker	Call entry (chapter 3)	Enter and update incidents; not send units (unless the agency allows it)
Police, fire, EMS dispatcher	The console with that discipline	Send and change their discipline's units (any, if the agency allows it)
Dispatcher (all disciplines)	The console	Everything on the floor
Supervisor	The console, the board (chapter 35)	Also intervene anywhere, reopen, read the ledger, run exercises
Administrator	Administration	Configuration; works the floor only when signed in for a floor duty
Records	Records (chapter 39)	Review views and records requests; changes no incident

A supervisor covering a position keeps supervisory rights. You are never asked which console you are at: an enrolled workstation (chapter 82) gives the position; a browser that is not one keeps a web position of its own (WEB- and four letters).

One-time codes. When the agency asks for them (Settings › Roles and sign-in), the first sign-in shows a QR code: scan it with any authenticator app and type its six digits. After that, type the current code each time; a code works once. An administrator resets it for a lost phone.

The lock. Ctrl+Shift+L, or the agency's minutes without input, locks the console: nothing is shown or changed until you unlock it with your password (and code). Everything stays open underneath, including what you were typing. Signing in and out, locking and unlocking are all in the ledger, with the duty and workstation.

> Before relying on these for criminal justice information, confirm your state's CJIS and access requirements.

CHAPTER 3

Call entry: the call-taker’s workspace

In the web interface: `/taker`

A calm workspace for one call: the call list on the left, nine tabs across the top with only the chosen one shown, and the call (its location, transcript and what was heard) with the **narrative** always on the right.

Key	Does
F4 or Ctrl+Enter	Submit the incident; after it, save changes to it
F2	Clear for the next call (asks first if anything is unsubmitted)
F6	Rebid the caller's location
F8	Write in the narrative
F3	CAD search
Alt+1 … Alt+9	Change tab

Call Entry. Type a code or a word for the call type (hundreds are fine; arrows and Enter choose), the priority (the type's, or another), **modifiers** (weapons, in progress, entrapment…: some raise the priority, some add people to notify, officer-safety ones show red), the incident's location (pick a suggestion, right-click the map, or use the caller's ALI position; **Verify** when the caller confirms it), the caller and callback, and where the caller is when not at the incident. The call's ANI/ALI is beside it.

Before a second incident. F4 first looks for open incidents at the same address, nearby or from the same callback. If there are any you see them: **Add this call to it** puts the call (and what you wrote) on that incident; F4 again makes a new one.

After submission the workspace stays on the incident. Dispatch has it at once; keep typing: comments go straight on it, and F4 saves changes to the type, priority, location or caller. A newer caller location (a rebid, a location provider) shows at the top: **Use it** changes the incident's location (the old one stays in the timeline, dispatchers and units are told); **Keep** leaves it.

The other tabs. Persons and **Vehicles** (several of each, with their role; what the caller said is offered to fill them), **Previous** (earlier incidents linked by address, phone, names, plates and VINs, confirmed or possible), **Hazards** (premises at and near the place, officer-safety people and modifiers, BOLO matches: the critical ones also show as one red line on every tab), **CAD Search**, **Comments** (every note in order, and logging mutual aid and resource requests, transfers, referrals, outbound calls and instructions given), **History** (units and their times, radio, the response recommended) and **Resources** (the agency's approved guidance (chapter 4)).

Notes written before submission keep their own time. Nothing is lost on a lock or a reload: the entry is kept in the browser tab until it is submitted or cleared.

CHAPTER 4

Resources: approved guidance with the call

As the call type, modifiers and what is said change, the **Resources** tab finds the passages of the agency's approved policies, call-taking guides, response guides and checklists that apply, and lights up when there is something new. Each passage shows its document, section, version and effective date, whether it is **policy (mandatory)**, a guide, a checklist or suggested prompts, and why it matched; **The whole document** opens the full approved text at that section. Outdated passages and two policies that both apply are marked. When nothing applies it says so.

Only approved text is shown, word for word; nothing is generated. Opening the tab records which passages, at which versions, were shown for the incident, so a reviewer later sees what was available at the time. Documents are kept in Approved guidance (chapter 86).

CHAPTER 5

The dispatcher screen

In the web interface: `/`

Everything a dispatcher needs is on one screen, and every part of it shows something useful.



Figure 2. The dispatcher screen: calls and incidents on the left, the map in the middle, the selected incident on the right

Area	What it shows
Status bar	Calls waiting, pending and active incidents, units available by discipline, the clock, and the health of every interface (BitVoice, radio, ALI, map, ledger)
Queue (left)	911 calls, ringing first, with callback, location, uncertainty and age; incidents by priority with their timers
Map (centre)	Units by status, incidents, caller locations with uncertainty, road routes of recommended and assigned units with arrival times
Unit board (bottom)	Every unit by discipline: status, time in status, incident, AVL age; overdue timers in amber. **Drag a unit onto an incident** in the queue to send it; **right-click** a unit for its statuses, sending it to the selected incident, and moving it up
Right panel	The selected incident (recommendation, units, timeline, caller), or when nothing is selected the situation: what waits for units, overdue timers, move-ups (chapter 20), coverage by station, recent activity
Command line (bottom)	Type anywhere to start a command (see The command line (chapter 30))

Select an incident by clicking it, with `[` and `]`, or from the palette (`Ctrl K`). `Esc` clears the selection.

CHAPTER 6

Your own layout

The dispatcher screen shows only the sections you want, where you want them. Someone new can start with two and add more when ready.

Open **Layout** at the top left of the status bar.

- **Ready-made layouts**: three for the duty you signed in as, drawn as small pictures. One click shows one. Every duty has **Getting started**: just the calls and the incident being worked.
- **Sections**: calls and incidents, map, incident, unit board, fire houses, police board and the command line. Click one to add it or take it away, or drag it onto the screen.

While the layout is **unlocked** (the lock button beside Layout, amber when unlocked), each section has a title bar:

To	Do
Put a section beside, above or below another	Drag it (from Layout, or by its title bar) to that edge of the other; the highlight shows where it will go
Make two trade places	Drop one on the middle of the other
Resize	Drag the line between two sections
Take one away	Its ✕
Start again from nothing	**Clear the screen** in Layout

Sections snap into place: nothing overlaps and nothing is left empty. **Lock** the layout when it is right: nothing can be moved, resized or taken away until it is unlocked again. Everyone starts locked on their duty's first ready-made layout.

Each person's layout is kept per duty, in this browser. The status bar and the emergency banners are always shown. The layout lock is not the screen lock (Ctrl Shift L), which hides the screen until you sign in again.

CHAPTER 7

The full console

In the web interface: `/console`

#/console always opens the full dispatcher screen, whatever duty you signed in for: a call-taker can look at the whole board there, and come back to call entry (chapter 3) at **#/taker**.

CHAPTER 8

Dispatching: reasons, warnings, plans and acknowledgement

- **Send rec** on a pending incident in the queue dispatches its recommendation in one press.
- **A reason.** Sending units other than the recommendation asks why (quick choices, or your own words); on the command line write it after a slash: `D E5 / closer by radio`. The reason and the response plan followed are kept with the dispatch.
- **Warnings.** When the location is not verified, is uncertain or is missing, the recommendation says so and you confirm before sending.
- **Response plans.** When a plan (chapter 75) applies, its due order leads; a planned unit that cannot go is struck through with why, and the unit going instead says whose place it takes. When the recommendation changes, the change is shown until you mark it seen.
- **Acknowledgement.** A dispatched unit that has not acknowledged in the agency's seconds flashes **NO ACK**; press it (or `ACK E1`) when it does. A crew acknowledges on its terminal.
- **Call entry facts** on the incident: modifiers, people and vehicles, a changed location (in amber for half an hour), where the caller is, BOLO matches, the talkgroup (`TG FIRE-OPS2`) and notifications still to make, each with **done**.
- **Situation**: the shift **passdown** log, active **BOLOs** (issue, cancel; `BOLO text` on the command line; crews see them) and **facilities** with one-press open / diversion / closed.

CHAPTER 9

Screens on several monitors

A position can spread its work over as many monitors as it has. Each monitor shows one **screen**: a window of the same live picture, arranged for one job. All of a position's windows share one sign-in and one selection: choose an incident on the queue screen and it opens on the incident screen and the map.

Open **Screens** with the monitor button on the status bar, from the command palette, or with **Ctrl+Shift+S**.

Screen	For
Incidents and call entry	911 calls and incidents beside the incident being worked; F2 for a new incident
Fire houses	Every station, its apparatus, who is covering and the empty houses
Police status and mark-outs	Every car: what, where, how long, and when its status check is due
Unit status	The unit board, large
Map	The map alone, following the selection
Incident and situation	The selected incident in full, or what needs attention
Supervisor board	Totals at a glance, read-only

- **Add a screen**, choose its **disciplines** (all, fire, EMS, police, other) and **Open** it. **Open all** opens every one.
- **Detect monitors** (Chrome and Edge) shows the monitors as the computer arranges them; give each screen its monitor and it opens there, filling it. In other browsers drag each window where you want it once: it opens there next time.
- The layout is kept on the workstation for the position, so the next shift at the desk gets the same screens. With **Offer to open these screens at sign-in**, the full console offers them in one click after signing in.
- The browser asks to allow pop-ups (and, in Chrome and Edge, window management) the first time.

Disciplines

A screen limited to some disciplines shows their units, and the incidents that need them: an incident's own call type, the units sent to it, and the units its run card asks for (a crash with injuries is on the fire screen and on the police screen). The status bar shows the screen's disciplines as a coloured chip. Every screen still shows every **emergency** and every 911 call not yet on an incident.

CHAPTER 10

Incidents and call entry screen

In the web interface: `/screen/calls`

The queue of 911 calls and incidents, with the incident being worked beside it at full height, the new-incident form (**F2**) and the command line. It is the call taker's and dispatcher's working screen when the map and units are on other monitors. Everything works as on the full console (see The dispatcher screen).

CHAPTER 11

Fire houses screen

In the web interface: `/screen/stations`

Every station as a card, with every unit that lives there or is covering there.

- **The bays**: one door per unit. Shut and green, it is in quarters and available; open, the stripe is the colour of its status.
- **The state**: IN QUARTERS (all home), PARTIAL, COVERED (a move-up is in) or EMPTY (no unit available in the house, with how long).
- **Tiles**: each unit's status, its time in it, and what it is doing (its incident, or where it is covering). Click, drag onto an incident or right-click as on the unit board.
- **Gaps**: a kind of unit the house should keep in quarters but does not, with the best **Move up** in one click (see Move-ups).
- Across the top: houses with a unit in, empty houses, units out, and each kind of unit available out of its total, with every status in a bar.

CHAPTER 12

Police status and mark-outs

In the web interface: `/screen/police`

Every police car in one table, with the map beside it: what it is doing, where, for how long, and when its **status check** is due.

- **Doing**: its incident (click to open it), or its **mark-out**: what it is doing on its own, such as a meal, court, fuel, a report or a follow-up.
- **Where**: the place given when it was marked out, its incident's address, or the nearest address to its AVL.

- **Status check**: a ring fills as the unit's time runs; amber near the end, red and flashing when the check is due, with how long past. A check is due after the status timer (Admin › Settings), or the mark-out's own time.
- **OK** records the status check (the unit is all right) and starts its timer again. **MO** marks it out; **AV** makes it available.
- The tiles across the top count available, on calls, marked out (by kind), out of service and checks due; click one to show only those.

From the command line

- `MO 2A12 MEAL 315 Church Ave`: mark out, with where. Without a place the unit's AVL position is kept. Add a note after a slash: `MO 2A15 COURT 315 Church Ave / Courtroom 2`. `MO` alone lists the agency's kinds.
- `SC 2A12`: status check, all right. Several units at once: `SC 2A12 2A13`.

Mark-outs are also on every unit's right-click menu and in the unit details, and a crew marks itself out from the mobile terminal (**F7**). A mark-out that can be pulled (a meal, a report) is offered by the recommendation when no available unit can fill a line: it is never sent without a dispatcher choosing it. The kinds, their times and which can be pulled are set in Admin › Settings.

CHAPTER 13

Unit status screen

In the web interface: `/screen/units`

The unit board on its own, with larger tiles that also say what each unit is doing. Click, drag and right-click work as on the unit board of the full console.

CHAPTER 14

Map screen

In the web interface: `/screen/map`

The dispatch map alone. It follows the incident or call selected on any of the position's screens, and draws marked-out units where they were marked out when their AVL is not fresh.

CHAPTER 15

Incident and situation screen

In the web interface: `/screen/incident`

The selected incident at full height (its calls, units, timeline, premises, recommendation and report), or, with nothing selected, the situation: what is waiting, status timers past due, move-ups and activity.

CHAPTER 16

911 calls

Calls arrive from BitVoice's event stream, from EIDO pushed by any call-handling system, and from the ALI spill. The same call from several sources is merged into one line.

- **Ringing** calls show before they are answered, so the dispatcher sees what is coming.
- **Location**: the caller's position and uncertainty circle, the address when there is one, and **STALE** when the location is older than the setting in Admin › Settings. Rebid asks for a new one (BitVoice).
- **+ Incident** on a call creates an incident from it, with the location and callback filled in. Calls already attached show their incident.
- Text to the caller, a video link and live video are on the call when BitVoice offers them.
- Its transcript (chapter 41) and what was heard, translation (chapter 42), the device location and floor (chapter 43), crash data (chapter 46), callers grouped (chapter 44) and non-emergency (chapter 45) calls are described in their own chapters.

CHAPTER 17

Incidents

New incident: `F2`, the New button, + Incident on a call, right-click on the map (the address is filled in), a search result's New incident, or `NEW SF 2001 Crystal Spring Ave` on the command line. An address the recorded map knows exactly is placed on the map at once, so units are ranked by road straight away; anything else stays text to be placed.

The incident panel shows the recommendation, the units on it with their times, the caller and the timeline. Notes (`N text`) and priority notes (`PN text`) go on the timeline; priority notes are shown to every dispatcher and unit.

Close with a disposition (`CL Handled`); units still on it become available. Supervisors can reopen (`RO #26-000123 reason`).

Correct the record (supervisors, on a closed incident) changes the call type, priority, disposition, address or a unit's times without reopening it: say why, and the timeline keeps what each was. Reports already sent (NERIS, NIBRS) are sent again by hand.

Replay (supervisors, on a closed incident) plays it back from the ledger: the units move on the map along their recorded positions (about every 30 seconds) while the timeline fills in, at 10× to 120×, with a slider to any moment.

CHAPTER 18

Unit recommendations

For the selected incident bitdispatcher builds a recommendation from its call type's run card: for each line ("3 × engine", "1 × als"), the available units with that capability, closest first. Units already on the incident fill lines first, and scarce capabilities are filled before common ones so a multi-role unit is not spent where another would do.

- **Drive times** come from the recorded road network: posted or typical speeds, one-way streets obeyed, from the unit's fresh AVL position or its station. The reason says so: "1.7 mi by road, 4 min via Franklin Road".
- Outside the recorded map, or with no road between, the time is a straight-line estimate and is marked `~` .
- A unit covering another station is ranked from where it is posted.
- Notes warn when no unit has a capability (consider mutual aid) or when sending the units would leave a station empty.

The recommended units are picked; **Dispatch** (`Ctrl Enter` , or `REC`) sends them. Click units to change the pick, **Use recommendation** to go back to it, or type `D E1 M2` . The ledger records what was recommended and what was sent.

CHAPTER 19

Advisory suggestions

Beside the incident and on the Situation panel, the advisory panel may suggest something: two incidents that may be the same, a call that may be about an open incident, words that do not fit

the call type ("smoke" on a fire alarm, "not breathing" on a fall), a repeat address, a priority 1 still without a unit, a unit on scene not heard from.

- **Why**: open a suggestion to see the evidence it relied on (with its source: unit, caller, dispatcher, machine), what it assumed absent, and the rule in plain words.
- **Cannot determine** is an answer: when sources of equal weight disagree ("smoke" and "no smoke" from two callers), it says so and you decide.
- **Accept** runs the suggested command as you (change the type, attach the call, dispatch the recommendation), or just notes it. **Reject** with a one-click reason; it is not shown again. Both are recorded.
- It advises only. It never merges, retypes, reprioritises or dispatches by itself, and core dispatch works the same when it is off or down.

When an upgrade supplies a new rule (such as *Silent or abandoned 911 call*), Admin › Advisory panel offers it above the rules: **Add it**, then **Save version**. A saved codebook never changes by itself.

CHAPTER 20

Move-up and cover

When a station has none of a kind of unit it normally houses available (its engine is out on a call), the Situation panel shows a **Move-up** box with the move that fills the gap: the nearest unit of that kind by road, from a station that can spare one.




Figure 3. A move-up: Station 1 has no engine, so E4 covers it from Station 4

- **Move E3 from ST3** posts the unit at the empty station in one click (`MU E3 ST1`). It stays available and is recommended from there.
- A move that would leave its own station empty is offered only after moves that empty nothing, and says "empties ST4".
- When the station's own unit is back, a **Home** button sends the cover home (`RET E3`).

- Which kinds are kept covered is set per unit type in Admin › Settings (front-line engines, ladders, medics, ambulances and patrol by default).

CHAPTER 21

Unit statuses

Code	Status	Meaning
AV	Available	In quarters or in service, can be sent
DP	Dispatched	Sent, not yet acknowledged
ER	En route	On the way
OS	On scene	Arrived
TR	Transporting	Taking a patient to hospital
AD	At destination	At the hospital
OOS	Out of service	Not available

Each status has a timer (Admin › Settings); a unit past its timer turns amber on the board and is listed under Status timers past due. Statuses are given on the command line (`ER E1` , `AV E1 M2`), from the unit's tile, or by the crew on the mobile terminal (chapter 32). AVL positions older than the stale setting are drawn dashed and not used to rank units.

CHAPTER 22

The dispatch map

The map is drawn from bitdispatcher's own recorded map (chapter 76): roads by class with route shields and one-way arrows, county and town lines, house numbers and hydrants at street level, fire, police, EMS and hospitals in their own colours.

- **Search** (top right): an address (`2001 Crystal Spring Ave`), an intersection (`Orange & Williamson` , `and` , `/` or `at`), a street, or a place. Arrow keys and Enter; New incident from a result. A house number not on file offers the nearest numbers on the same street.
- **Right-click** anywhere: what is here (the nearest address or road), New incident here, and Views of this place (chapter 24) when a provider is on.

- **Routes**: for the selected incident, the road route of each recommended, chosen and assigned unit, with its arrival time on the unit.
- **Day / Night** switches the palette; **Photos** (F7) puts aerial photos under the streets; **3D** stands the buildings up (OpenStreetMap's storeys where mapped) and tilts the map, and right-drag turns it; **Fit all** shows every unit and incident; OOS and Stations show or hide those.
- The dashed cyan line is the edge of the recorded map: beyond it the online map is shown, muted, and drive times are estimates.

CHAPTER 23

Aerial photos

Dispatchers find places by rooftops ("the white house behind the church"). With **Photos** on (F7 or the button on the map), aerial photos are the base and the streets, names and house numbers are drawn over them.




Figure 4. Aerial photos are recorded in two levels of detail

- Photos are recorded in Admin › Map: full detail near the centre, less detail out to the edge. Zooming in past what was recorded enlarges the photo below it, so the map never goes blank.
- The chip beside the button says when the photo at the map centre was taken, where the source publishes it ("2023, 12 inch ortho"): an old photo is never taken for today.
- Where nothing is recorded the server fetches the photo when asked and keeps it, unless that is switched off.

CHAPTER 24

Views: the place from every side

Aerial photos show the roof. **Views** show the front, the back and the sides: where the back door is, the fence, the stairs, the side the hydrant is on.

- **Views** on the incident panel (beside the location), in the call-taker's **Hazards** tab, on the crews' mobile terminal (chapter 32), and from a right-click on the map.
- **N E S W**: the four oblique aerial photos, looking north, east, south and west, from the agency's own EagleView licence. Looking north shows the south side of a building. The arrow keys turn the compass.
- **Street** photos that look at the place, nearest first and at most two per direction, from Panoramax or Mapillary (open photos, CC-BY-SA, coverage depends on who has photographed the street).
- **Pre-plan** photos: the agency's own pictures of a premise (the Knox box, the gas shut-off, the rear entrance), offline and on this server. Crews add them from the terminal with the device's camera, dispatchers and administrators from here or Premises (chapter 84); supervisors remove them.
- Every picture says where it came from and when it was taken, so an old picture is never taken for today. The expand button shows it full size.
- **Google Street View**, when offered, opens Google in a new tab; nothing from Google is shown inside bitdispatcher.

> Looking a place up tells the provider where the incident is. Each provider is off until an administrator turns it on in Integrations (chapter 79), and the pictures pass through this server, so keys never reach a browser.

CHAPTER 25

Messages to and from the crews

Messages go from the floor to the crews' terminals, and from crews to dispatch or to another unit, without the radio.

- **Write** in Messages (Situation panel): to one unit or several (`E1 M2`), a discipline (`ALL-FIRE` , `ALL-EMS` , `ALL-POLICE`) or everyone (`ALL`). Leave To empty to write to the units on the selected incident. **!** makes it urgent.
- **Command line**: `MSG E1 M2 / Stage at the north lot` , `MSG ALL-EMS ! Carilion on diversion` , `MSG #26-000123 / Caller says the back door is open` .

- **From the crews**: messages to dispatch are bold until a dispatcher clicks them, and announced as they arrive. A message on an incident is also written on its timeline.
- **Read**: the terminal marks a message read when it is shown (an urgent one when the crew presses Got it); the floor sees *read by E1*, or *not read yet* after two minutes.
- Every message and every read is a ledger event. Crews write to dispatch or to units, never to everyone.

CHAPTER 26

Alarms, plate readers and gunshot detection

Alarm companies, plate readers and gunshot detection send their alerts to bitdispatcher (Admin › Integrations; the contract is docs/ALERTS.md). Each arrives in the 911 calls list as a call, **data only**, with what it is at a glance: the alarm type and zone, VERIFIED when the alarm company verified it, the plate and its hotlist, the number of rounds.

- Select it: the incident panel shows everything the sender gave (premise, account, permit, keyholder, the operator's call-back line, the camera and heading, a link to the reader's picture).
- Make the incident from it, or attach it to one, as from any call; the agency's own alarm and shots-fired types are suggested when they exist.
- An update from the sender changes the same call; a **cancel** from an alarm company goes on the incident as a priority note.
- Alarm companies are told what became of their alarm: accepted, dispatched, on scene, closed.
- An alert nobody acts on leaves the queue after 30 minutes; it stays in the ledger.

> ASAP over Nlets, the national standard for alarms, is not connected yet: it needs the standard's schema and the state's message switch.

CHAPTER 27

The station screen and toning out

In the web interface: `/station`

When units are dispatched, their stations are toned out (where an administrator turned it on in Integrations). In the firehouse, a screen on a read-only account at **#/station** (choose the station once; it is remembered) shows the station's units and their statuses, and on an alert:

- rising **tones**, twice as many for a priority 1, then the call **read aloud** twice: the units, the call type and the street;
- the call in large type: priority, type, address, the units, the latest priority notes;
- **Acknowledge** stops it and puts *ST1 acknowledged the alert* on the incident; **Read it again** repeats it.

Press **Press to turn the sound on** once after the screen opens (browsers play sound only after a press). The inactivity lock leaves a station screen on a read-only account alone.

- `TONE` on the command line tones out the stations of the units on the selected incident again (`TONE E1`, `TONE #26-000123`); each tone-out is on the incident's timeline.
- An alerting controller from a vendor gets the same alert at its address (docs/STATION-ALERTING.md).

CHAPTER 28

Incidents with neighbouring agencies

Incidents go to and come from neighbouring agencies' CADs as EIDOs, the NENA standard (Admin › Integrations › Neighbouring agencies; docs/CAD-TO-CAD.md).

- **Send**: on an open incident, **Send to a neighbouring agency…**, choose the agency and say why (*mutual aid, need a ladder*; *on your side of the line*). It goes with the location, the callback, our units on it and the notes; the timeline says it was sent.
- **Receive**: what a neighbour sends arrives in the 911 calls list as a call from that agency, data only, with their incident number, type and notes. Make the incident from it or attach it as from any call.
- Each send is a press: closing and unit status do not flow back on their own yet.

CHAPTER 29

Files and photos on an incident

An incident keeps files: a crew's photos of the scene, a PDF, an audio or video clip.

- **Add**: on the incident panel, **Add** (with a caption if you like); on the mobile terminal, **Photo or file** opens the camera. Crews add to incidents they are on. Up to 25 MB each: pictures, PDF, plain text, MP3, WAV, MP4, WebM. The server goes by what the file is, not its name.
- Pictures show as thumbnails (click for full size); others open or download. Each file is on the timeline with who added it.

- Each file's SHA-256 is in the ledger: a file changed on disk is refused, not shown.
- A supervisor removes a file with why. It stays in the record, hidden from everyone below supervisor.

CHAPTER 30

The command line

Type a letter anywhere on the dispatcher screen and the command line takes it (or press `/`). `Tab` completes, arrow keys recall earlier commands, results stay on screen. `HELP` lists every verb.

Command	Does
`D E1 M2`	Dispatch units to the selected incident (`D E1 #26-000123` names one)
`REC`	Dispatch the recommendation
`ER E1` · `OS E1` · `TR M1` · `AD M1`	En route, on scene, transporting, at destination
`AV E1 M2`	Available: clears them from their incident
`OOS E5 brakes`	Out of service with a reason
`N text` · `PN text`	Note, priority note
`NEW SF 12 Main St`	New incident (`NEW CHEST P1 …` sets the priority)
`P 2` · `T VF`	Change priority or call type
`CL Handled` · `RO #26-000123 reason`	Close, reopen
`MU E4 ST1` · `RET E4`	Move up to cover a station; send home
`TG <talkgroup>`	Set the selected incident's talkgroup
`BOLO <text>`	Issue a BOLO for the selected incident, or none
`ATTACH <call> #26-000123`	Attach a 911 call to an incident
`ACK`	Acknowledge the emergency in the red bar (the newest)
`ALARM` · `ALARM 3` · `2ND`	Upgrade the selected incident to its next alarm (or a level); `REC` then sends the extra units. See Alarm levels (chapter 58)
`PAR` · `PAR MISSING E3` · `PAR FOUND E3`	Record a roll call of the crews on scene. See Accountability (chapter 60)
`BM UC`	Record a fire-ground benchmark (UC fire under control, PS primary search…)
`TOW` · `TOW heavy North / VA ABC-1234`	Call the next tow company on the rotation. See Tow rotation (chapter 62)
`PAGE <group> / text`	Page a responder group about the selected incident. See Paging (chapter 61)

Command	Does
`DIR water`	Look up the contacts directory. See Directory (chapter 64)

CHAPTER 31

Keyboard

Key	Does
Any letter	Starts a command on the command line
`/`	Focus the command line
`F2`	New incident
`Ctrl Enter`	Dispatch the units picked for the selected incident
`Ctrl K`	Palette: go to an incident, unit, screen or chapter of this manual
`[` `]`	Previous and next open incident
`Esc`	Clear the selection
`F7`	Aerial photos on or off
`F9`	NCIC inquiry, with the selected incident as the reason
`F1` – `F6` (mobile terminal)	En route, on scene, transporting, at hospital, available, out of service

PART 2

In the field

The mobile data terminal a crew uses from the vehicle.

CHAPTER 32

Mobile data terminal

In the web interface: `/mdt`

A crew signs in on the vehicle's laptop or tablet with a **field** account (Admin › Users) and the unit's call sign as the position (`E1`). The terminal opens at once.

- **The assignment**: type, priority, address in large type, the road route drawn on the map with its time and the roads it takes, the callback, the other units on it, and the notes from dispatch, newest first. Priority notes stand out.
- **Status buttons**: one tap each, with the usual next status highlighted; `F1` to `F6` on a keyboard.
- **Notes to dispatch** go on the incident's timeline as the unit's.
- **GPS**: the device's position goes to bitdispatcher as AVL every few seconds (allow location when the browser asks).
- **Emergency**: hold the button for two seconds. Dispatch sees the emergency banner and acknowledges it.
- **Photos** on the map, as on the console.
- **Messages**: what dispatch (or another unit) writes to this unit, with a reply line and quick replies (Copy, Delayed, Need PD…). An urgent message fills the top of the screen and sounds until the crew presses Got it; see Messages (chapter 25).
- **Take it**: where the agency allows crews to attach themselves (Settings › Roles), an available unit takes a waiting incident from the list in one press; it is recorded as a dispatch by the crew, self-attached.

A crew acts only as its own unit. Dispatchers can open the terminal at #/mdt to see what a unit sees (the position names the unit).

CHAPTER 33

Incident reports (RMS)

In the web interface: `/rms`

Officers and dispatchers write incident reports at #/rms, or with **Report** on an incident (the incident's location and time are filled in). A crew on a mobile terminal writes its own from the car.

- **Sections**: when and where (location type, whether it was cleared), offences, people, property, vehicles and the narrative. Codes are shown in words and picked in one click; the screen asks only for what the offence needs (a weapon for an assault, the method of entry for a burglary, the drug for a seizure, the injury and the relationship to each suspect for a crime against a person).
- **Saved as you type**: a draft saves itself a moment after typing stops.
- **Before it is submitted** lists what is still missing for incident-based reporting: the FBI's NIBRS data elements and edits, with Virginia's additions (property quantity, the licence plate reader indicator, drug types). Submit is available once the list is empty.
- **Approval**: a supervisor other than the author approves it, or returns it with what to fix. Every save and decision is a ledger event.

The state file

Supervisors see **State IBR file** under the list. Choose the month and press **File**: bitdispatcher writes the month's approved reports in Virginia's incident-based reporting format (the FBI's position-based flat file with Virginia's additions, 2025.2 specification): Group A incidents with their offence, property, victim, offender and arrestee segments, Group B arrests, or a zero report when there is nothing. Upload it to the Virginia Crime Repository by the 15th of the next month. Reports that fail the checks are left out and listed. Making the file is a ledger event, with its SHA-256.

Format: FBI national writes the same reports in the FBI's own flat-file layout, without Virginia's additions, for states that take the national file. That file has been checked with SEARCH's NIBRS Pre-Certification Tool validator, which applies the FBI's edits (`scripts/nibrs-validator.sh`); passing it is not FBI or state certification.

> The settings need the agency's nine-character ORI (Admin › Settings). Before the first production upload, the Virginia State Police ask for a test file by email (dart@vsp.virginia.gov).

Draft from the incident (on a report written from an incident) fills the narrative with a first draft: the type, place, times, units, people, vehicles and notes from the record. With the language model on (Admin › Integrations) the model writes it from the same facts and is told to add nothing, writing *[to be completed]* where something is missing. Either way it is a proposal: check every line and finish it in your words.

CHAPTER 34

NCIC inquiries

NCIC (on the reports screen, F9 on the dispatcher screen, or on the mobile terminal) sends an NCIC 2000 inquiry through the state's message switch: wanted person (`QW` : name with date of birth, or name, sex and race), vehicle (`QV` : plate and state, or VIN), gun (`QG`) and article (`QA`) by serial.

- Each inquiry needs a **purpose** code and a **reason** (the incident number): CJIS requires both.
- The ledger keeps who asked, when, the purpose, the reason and whether a record came back. The terms are kept only as a fingerprint and the answer not at all.
- **A hit is a lead**: confirm it with the entering agency before any action.
- Administrators set the agency's ORI and the switch in Admin › Settings: off, the **training simulator** (plates, names and serials starting with TEST return a record; every answer says SIMULATED), or a switch adapter by TCP.

PART 3

Supervising

Reports built from the ledger, and the ledger itself.

CHAPTER 35

The supervisor board

In the web interface: `/board`

The whole picture at a glance, for a supervisor's second monitor or a wall display. It only shows: nothing on it changes anything.

- **Across the top**: 911 calls not yet on an incident (red when one is ringing), incidents waiting for a unit with their priorities and the oldest wait, active incidents, units available out of those in service, units marked out by kind, status checks due, and empty stations.
- **Where the work is**: the map shaded by how much is open in each area (open incidents plus twice those waiting), with each area's open, waiting and available units. Areas are the county's emergency service zones or beats when they are loaded (Admin › County GIS); otherwise each station's area, the part of the map nearest it. An area with incidents waiting and no unit free, or two waiting, is **SWAMPED**.
- **By discipline**: a ring of every status with the number free, and each kind of unit available out of its total.
- **Busiest areas**, worst first, and **new incidents** over the last six hours by priority.
- **People**: each signed-in position's workload and breaks, and the care list after critical calls. See Breaks and workload (chapter 51) and Critical calls and care (chapter 50). A possible line attack shows across the top (TDoS (chapter 56)).

Choose the disciplines across the top, or open it from Screens with them. **Full screen** is beside the clock.

CHAPTER 36

Operations report

In the web interface: `/admin/reports`

Admin › Operations report builds the Daily Operations Report and shift debrief for a period from the ledger alone: nobody retypes what CAD already holds.

- **Periods**: this shift, last shift (from the shift change times in Settings), today, yesterday, last 7 days, or any range.
- **Contents**: 911 calls, incidents, dispatches and closes; incidents by hour, type, priority and disposition; response times (call to dispatch, dispatch to en route, call to on scene, on scene to clear) as median and 90th percentile; priority 1 incidents; incidents open at the end (the turnover); status timers run out, once per episode; emergency activations and how fast they were acknowledged; each person's actions; unit demand by phase and utilisation; system and configuration changes.
- **Drill-down**: click any number to see the ledger events it is made of.
- **Certify**: once the period has ended, a supervisor certifies it with optional context. The certification is a ledger event with the report's hash; if anything changes later, the report says it changed since it was certified.

> Activity counts intentional actions only and is never a score: it shows workload, not performance.

CHAPTER 37

The advisory codebook

In the web interface: `/admin/advisory`

Admin › Advisory panel holds the codebook: the rules the panel uses, in plain words, with their thresholds.

- **Mode**: off; **shadow** (evaluated and kept in the ledger, shown to supervisors only, so the rules can be judged before anyone relies on them); **live** (dispatchers see suggestions). A new system starts in shadow.
- **Source precedence**: drag to order unit, caller, dispatcher and machine evidence, strongest first. A stronger source outweighs a weaker one; equal sources that disagree give "cannot determine". A silent alarm panel never outweighs a person who can see smoke.
- **Rules**: switch each on or off, set its severity, distances, times, words and the call types they already fit, and edit its explanation.

- **Test** replays the recorded ledger for the last day, week, month or quarter with the rules on screen, saved or not, and counts what each would have suggested.
- **Save version** keeps the change with a note; every version is listed and can be restored in one click. Decisions (accepted, rejected and why) are listed: rejecting a suggestion is never treated as an error.

Agency scripts

JavaScript script and **Lua script** add a rule that is the agency's own code, versioned, tested and switched between shadow and live with the rest of the codebook. A script defines one function for its hook:

Hook	Function	Returns
Each open incident	`advise(i)`	nothing, or `{title, detail, severity, action: {label, command}}` (or a list): a suggestion; accepting runs the command on the incident, as the person who accepts
Unit recommendation	`recommend(r)`	`{prefer: [unit ids], notes: [text]}`: a preferred unit among a line's next best takes a place; notes are shown with the recommendation
Incident reports	`check(r)`	a list of `{field, message}`: shown as **Agency checks** beside the state's; they advise and do not stop a submission

An incident script sees the number, type and its name, priority, status, address and position, minutes since it was created, notes, units on it, hazards at its premises, caller name and number of calls. **Try it** runs the script once on the newest real incident (or report) and shows what it returned, what it logged with `log()`, and how long it took; **show the input** shows exactly what it saw.

- A script has no files, network, process, environment or code loading: only its input and `log()`.
- It always has a time limit (50 ms unless set, at most 1 s). It runs after the CAD's state is released, so a slow script never holds dispatch up.
- A script that fails or runs out of time is shown under its rule and in the test; the panel and the recommendation carry on without it and say so.

CHAPTER 38

Ledger and audit

In the web interface: `/admin/ledger`

Every action that changes state, takes attention or creates accountability is an event in an append-only ledger: who (user, role, position, session), when, what, on which incident, unit or call. Each event carries the hash of the one before it, so a change anywhere breaks the chain.

- **Verify** checks the whole chain and reports the first broken link, if any.
- **Search** by type, person or text; events are newest first.
- The current state is rebuilt from the ledger at every start, and reports are built from it.

CHAPTER 39

Records and requests

In the web interface: `/records`

The records area reads a finished incident and answers requests for it, all from the same tamper-evident ledger (chapter 38) the rest of the system writes to.

Reviewing a record

The review screen shows one incident four ways, and opening or exporting a view is itself recorded in the ledger.

View	What it shows
As first entered	The incident as it was first created, before any later change
Summary	The short account
Detailed	Everything on the incident
Full audit	Every ledger event, with a hash-chain check: it confirms the number of events and reports any break

Print or **Download text** keeps a copy; both are recorded. Open any incident by its number.

Records requests

A request names a requester, a contact, what is asked for, the incidents, and whether the **summary** or **detailed** view is released. Each request shows the working days left until it is due (amber when close, rose when overdue) and the working time taken so far.

1. **Assemble** builds the release copy from the chosen view and proposes redactions by the agency's disclosure rules; the original record is untouched.
2. For each incident, accept or reject each proposed redaction, giving the **basis** required for anything withheld, or **mark a passage** by selecting it in the record. A live preview shows the redacted copy.
3. **Save decisions** records every decision, accepted and rejected.
4. **Approve and release** is the moment a person authorises the release: accepted redactions are applied permanently and the copy is checked for leaks before it leaves. A released copy can then be downloaded, and its hash is shown.

> Records work needs the records duty, a supervisor or an administrator.

CHAPTER 40

Disclosure rules

In the web interface: `/admin/disclosure`

Disclosure rules are the agency's legally reviewed rules for records requests (FOIA). Nothing is hardcoded as exempt; the system proposes, people decide, and your counsel reviews every rule before it is enabled.

A rule has an id, name, jurisdiction and record types, and matches by:

- **Category**: a named category of the record.
- **Words**: any of a comma-separated list.
- **Pattern**: a Go regular expression.

A **legal basis** is required, with an explanation, an optional effective window, and an enabled switch. A rule stays disabled until counsel has reviewed it.

- **Add the sample rules (disabled)** loads examples; they are examples, not legal advice.
- **Try it** pastes a record's text and shows it with the proposed passages highlighted — amber where the confidence is "review", rose where it is "high" — and a list of each with its text, rule, basis and confidence.

PART 4

What 911 centres asked for

Transcripts and translation, callers grouped and screened, crash data, drones, care for the people, training, quality review, outages and line attacks.

CHAPTER 41

Transcripts and what was heard

When call handling transcribes calls, each call shows its **transcript** live, the caller in white and the call-taker in blue, and **Heard on the call**: the details pulled out of it, so the call-taker types less.

- **What is pulled out**: the address, weapons, vehicles, plates, the direction someone went, how many people, injuries (not breathing, unconscious, bleeding), hazards (fire, trapped, gas, a dog, an electric car) and the caller's name. Urgent ones are red and come first, and show on the call in the queue.
- **Use**: on an address, places the call's incident there (a map search, exact when the map knows the number; check it on the map). Before there is an incident it copies the address.
- **Where transcripts come from**: BitVoice's live transcript when it sends one, its transcript of a recorded call afterwards, or any speech-to-text engine posting to the transcript hook (Hooks (chapter 57)).
- Rules, not a model, pull out the details: the same words always give the same details, and each shows the words it came from.

> A transcript is what a machine heard. The call-taker's own judgement and questions still decide.

CHAPTER 42

Callers in another language

A caller speaking Spanish is translated line by line on the transcript, marked **Spanish · translated**; **Show original** shows what was said.

- **The phrasebook** built into bitdispatcher translates the words of emergencies between Spanish and English, offline. When it knows too few of a line's words it says **gist only**: get an interpreter.
- **Say it in Spanish**: press a ready phrase (Help is on the way, Is the person breathing?, Get out of the house now…) or type in English; the translation shows as you type. It is kept on the transcript, texted when **also text it** is ticked (BitVoice), and the speaker button says it aloud on this console.
- **A language model** (optional, Admin › Integrations) translates what the phrasebook cannot, on an OpenAI-compatible chat API: one on your own server, or a service under your agency's agreement. What callers say is sent to it, so it is off until an administrator switches it on.

CHAPTER 43

Where the caller is: device location and floor

Each call says how its position was found: **device location** (the phone's own fix, often a few metres, the FCC's dispatchable location), GPS, cell sector or on file.

- **Floor**: a civic floor from call handling, and the **altitude** of a 3-D fix with its uncertainty, which tells which floor of a tall building.
- **Trail**: a caller who moves leaves a dotted trail on the map of every position received, the selected call's brighter.
- **Rebid** asks for a new position; **STALE** marks an old one (Admin › Settings).

CHAPTER 44

Many callers, one incident

When several people call about the same thing, the queue groups them under **N callers about one place**: calls near each other (300 m by default) within a short time (10 minutes).

- Make the incident from one call; the group then offers **Attach N to** that incident, one press for the rest.

- With an incident selected, the group offers to attach all of them to it.
- Calls already on different incidents are never grouped together. Change the distance and time in Admin › Settings (chapter 78).

CHAPTER 45

Non-emergency calls

Calls on a **non-emergency line**, or whose caller says something that is seldom an emergency (a noise complaint, parking, a power outage), go to the **Non-emergency** list under the 911 calls, with the reason.

- Anything urgent said on the call (a weapon, not breathing, fire) keeps it an emergency, whatever else was said; so does crash data.
- **It is an emergency** moves it back; a person's decision always stands and is recorded.
- **Send the usual reply** texts the reply set in Settings, such as where to report online.
- Set the lines, the words and the reply in Admin › Settings (chapter 78).

CHAPTER 46

Vehicle crash data

A vehicle's automatic crash notification arrives as a call with **CRASH DATA**: the vehicle, delta-V (the change of speed in the crash), the direction of the impact, rollover, airbags, occupants and belts, and its power (electric, hybrid).

- **Injury risk** is high for delta-V of 40 km/h (25 mph) or more, a rollover, or 20 km/h with no belt, several impacts or a side impact; medium for 20 km/h or any airbag. Suggestions follow: ALS, extrication, air medical, more than one ambulance, and for an electric car a word to the fire crews.
- It is a rule of thumb from field-triage criteria to help pick the response, not a diagnosis. Change the thresholds in Admin › Settings (chapter 78).
- Crash notifications reach bitdispatcher through the crash hook (Hooks (chapter 57)).

CHAPTER 47

Drones

With a drone system connected (Admin › Integrations (chapter 79)), an incident on the map shows **Send a drone**. bitdispatcher sends the drone system the incident, its type, priority, position and summary; the drone system decides which drone flies.

- **Launch rule**: incidents of call types marked **Send a drone** (Call types) ask by themselves, once each.
- The drone reports back to the drone hook: its status, position, battery and live picture. It flies on the map, its status goes on the incident's timeline, and **Live picture** opens its video.

CHAPTER 48

Radio transcripts

When BitVoice or the radio system transcribes transmissions, a unit's words go on its incident's timeline in italics (`E1: on scene, smoke showing`), so the record holds what was said on the air. The words come with BitVoice's radio events, or through the radio-words hook (Hooks (chapter 57)).

CHAPTER 49

Incident summaries

Every open incident has a **Summary**: what and where, what the callers said that matters (the urgent first), the priority notes, the hazards on file at the place, who is on scene and who is responding, and a drone over it.

- It is built from the record by rules, so it says nothing the record does not; it changes as the incident does.
- It shows on the incident panel (Copy puts it on the clipboard) and at the top of the crews' mobile terminal (chapter 32).

CHAPTER 50

Critical calls and care

Some calls stay with the people who take them. An incident is a **critical call** when its call type is marked critical (cardiac arrest, shooting and stabbing to begin with) or when words such as not breathing, CPR, officer down or infant are said on it.

- Everyone who worked it (the call-taker and the dispatchers who entered, sent or noted) goes on the **care list** on the supervisor board (chapter 35), with the reason.
- The supervisor **offers a break** to each person, **arranges a debrief** (with a note of when and where) and marks it **Done**. Each is recorded.
- Once the incident closes, each person sees a quiet line on their own console: that was a hard call, take a moment, and the support line set in Settings. **Take a break** puts them on a break.
- Set the words, the support line and the call types in Admin › Settings (chapter 78) and Call types (chapter 74).

CHAPTER 51

Breaks and workload

The cup on the status bar puts you **on a break** and back; the supervisor board shows it.

The board's **People** panel lists every signed-in position: calls in the last hour, actions, time since the last break, critical calls in four hours, and a state:

- **watch**: two hours without a break (Settings), a critical call, or a very busy hour;
- **relieve**: three hours without a break, or two critical calls.

It names the least busy positions free to relieve someone.

CHAPTER 52

Training

Tick **Training** when signing in. The console opens a board of its own, marked TRAINING in violet: the agency's units, stations, call types, premises and map, on a ledger of its own. Each trainee has their own board, even on a shared account; one left idle for two hours is cleared. Nothing done there reaches the live board. Administration there is staging: an administrator's changes stay on the training board until published (see Exercises, injects and staging (chapter 53)); users, connections and maps are the live board's.

- **Scenarios** play calls, transcripts, crash data and radio traffic into it on the agency's own map: a house fire with three callers, a cardiac arrest in Spanish, an interstate crash with crash data, an armed robbery, and a flood of calls on the line.
- **Score** checks what was done: every caller on an incident, the call type, the units sent, a reply in the caller's language, and each incident's quality review (chapter 54).
- **Reset** empties your board and starts it again; other trainees' boards are untouched.

CHAPTER 53

Exercises, injects and staging

An exercise is one training board for everyone who joins it: tick **Training** at sign-in and type the exercise's name (any name; the first to join makes it). Trainees sign in with their own duties, so a call-taker, dispatchers and a supervisor work it together, and crews can join on the mobile terminal (chapter 32) the same way. Practising alone, leave the name empty.

The instructor (a supervisor or administrator) presses **Inject**: a new caller (where, who, and what they say as the exercise goes), the caller saying more or moving, a unit going out of service, an emergency button, or a unit on the radio. **Timeline** downloads every event for the debrief, and when the exercise ends its timeline is kept (Supervisors: `/api/exercises`).

Staging. An administrator signed in with Training changes call types, units, stations, response plans, guidance or facilities on the training board, tries them there, then opens **Staged changes**: it lists what differs from the live board; choose the parts, say why, and **Publish**. With *Change configuration only through staging* on (Settings), those changes cannot be made on the live board directly.

> The training board is not a backup of the live board. A continuity site is a separate, tested arrangement: see Several sites (chapter 83).

CHAPTER 54

Quality review

In the web interface: `/admin/quality`

Every incident checked against the centre's standards:

Check	Standard (Settings)
Answered in time	15 s, NENA's call-answering standard
Entered in time	answer to incident, 90 s
Dispatched in time	entry to the first unit, 60 s, priority 1 and 2
Location verified, callback, disposition	captured
Questions asked	heard on the transcript: the address, the callback, and by discipline (breathing and awake for EMS; anyone inside for fire; weapons, description and direction for police)

Each incident gets a score over the checks that applied; the page lists them for a period, each call-taker's average and each check's pass rate. Press an incident for its checks. A review is a coaching aid: a missed question may simply not be on the transcript.

CHAPTER 55

Working through an outage

Each console keeps the last board it had. When the server cannot be reached, an amber bar says so and the console shows that board, as it was, with the time. A console reloaded during the outage still opens.

- **Offline log**: new incidents, notes and unit statuses are kept in this browser, in order.
- When the server is back the bar offers **Send them now**: each goes in marked "entered offline at 14:02 by jlee"; anything the server refuses stays, with the reason.
- For a server that never goes away, run bitdispatcher at two sites (Several sites (chapter 83)): each keeps working when the other is cut off.

CHAPTER 56

Line attacks (TDoS)

A telephony denial-of-service fills the lines so real callers cannot get through. bitdispatcher watches the calls and raises **Possible telephony denial-of-service** on every console and the supervisor board when:

- far more calls arrive in a minute than usual (five times the last hour's rate, at least 12, or the number set in Settings);
- one number calls five times or more in ten minutes (shown as ×5 on its calls);
- eight or more silent or very short calls arrive in five minutes.

A supervisor **acknowledges** it; it clears after ten quiet minutes. Keep answering: a real emergency can be among them.

CHAPTER 57

Hooks and connections

Other systems send to bitdispatcher with `Authorization: Bearer` and the hook token set in Admin › Integrations (chapter 79). Without a token the hooks are off.

Hook	Sends
`/api/hooks/transcript`	`{"call": "id", "speaker": "caller", "text": "…", "lang": "es"}`, or `lines`: a call's words
`/api/hooks/acn`	a crash notification: JSON or key=value, common telematics names (delta_v_mph, pdof, rollover, airbag_deployed…)
`/api/hooks/drone`	`{"id", "status", "lat", "lon", "battery", "incident", "videoUrl"}`
`/api/hooks/radio-text`	`{"unit" or "radioId", "channel", "text"}`

The drone system's launch address and token, the launch rule, and the optional translation model are set on the same screen.

PART 5

Fire ground, crews and the police desk

Bigger fires, who is aboard each unit, roll calls, paging volunteers, tows, the schedule, the numbers to call, areas on the map, a unit’s day, patient-care reports, papers to serve and alerts to the public.

CHAPTER 58

Alarm levels: 2nd and 3rd alarms

A working fire outgrows its first run card. Each call type may have **further alarms** (Admin › Call types): the 2nd alarm, the 3rd, each adding units to what the incident needs. The first alarm is the call type's own run card.

Upgrading

- On the incident, **Upgrade to 2nd alarm** says what it adds (`+2 engine, 1 ladder…`); or type `ALARM` (`2ND` , `3RD` , `ALARM 3` for a level).
- The upgrade is a priority line on the timeline every dispatcher and crew sees, with what it adds.
- The recommendation then fills the bigger run card, counting the units already there, and `REC` (or Ctrl Enter) sends the extra units. Paging groups and station alerts follow the dispatch as usual.
- **Bring down** goes back a level, with a reason.

> Setting up: Admin › Call types › a type › Further alarms. Each alarm has a name and run-card lines (capability and count). The structure fire type comes with a 2nd and 3rd alarm to edit.

CHAPTER 59

Personnel and crews

In the web interface: `/admin/personnel`

The **roster** is the agency's people: a number, name, rank, qualifications (paramedic, EMT, driver, officer…), home station, and how to page them (a phone for texts, an email, a push topic). Add them one by one or **Import from CSV** (columns: id, name, rank, qualifications separated by ;, station, phone, email, volunteer).

Who is aboard

On any unit (the unit's panel › Crew › change) or from the crew's own terminal (**Crew**), pick who rides it this shift. A member is on one unit at a time: putting them on another moves them. The incident's timeline records crew changes on a unit working it.

What staffing changes

- **Minimum aboard** (Admin › Settings › Unit types, or per unit in Admin › Units): a unit below it is shown short-staffed, in the recommendation's reasons and on the supervisor's exceptions.
- **What a capability needs** (Admin › Settings › Crews): by default ALS needs a paramedic aboard. A medic whose recorded crew has no paramedic is not recommended for an ALS line (it is still BLS and transport).
- A unit with **no crew recorded** is taken as staffed: an agency that does not keep rosters here sees no change.

> Dispatchers see the roster without phone numbers and emails; supervisors see them.

CHAPTER 60

Fire-ground accountability: roll calls (PAR)

At a working fire the incident commander takes a **roll call** (a PAR) of every crew on scene at set intervals, and dispatch keeps the clock.

- A call type marked **Fire-ground accountability** (Admin › Call types) starts the clock when the first unit arrives on scene; **Start roll calls** starts it on any fire incident.

- The incident shows the time since the clock started and when the next PAR is due; it turns amber when overdue, and the supervisor's board lists it.
- **All accounted for** (or `PAR`) records a roll call of every crew on scene. A crew that did not answer: click it, then **Report … missing** (or `PAR MISSING E3`). That is a red, flashing line on the incident and an urgent exception for the supervisor until **E3 found** (`PAR FOUND E3`).
- **Benchmarks** the commander reports (primary search complete, fire under control, loss stopped…) are one click each, or `BM UC`, with the time since the incident started.
- The clock stops when the incident closes; it cannot be stopped while a crew is missing.

> The interval is 20 minutes unless changed in Admin › Settings or on the call type.

CHAPTER 61

Paging responders

In the web interface: `/admin/paging`

Volunteer and off-duty firefighters and EMTs are called by **page**. A **paging group** says who is paged together and how:

- **Members** from the roster (Personnel (chapter 59)).
- **Gateways**: how pages go out, set up by an administrator in Admin › Integrations › Paging: a text by Twilio, an email, a push to phones by ntfy, a webhook, or IamResponding and Active911 (both take dispatch by email in their documented formats).
- **Automatic**: page the group when one of its units or stations is dispatched, or when an incident of one of its call types gets units. Each group is paged once per incident by its rule.

A page

The page's subject is the call type and address, the text the incident's summary and units. Each person gets a link to answer: **Responding to the station**, **Going straight to the scene**, or **Not available**, with when they expect to arrive. No sign-in: the link is the key, and works only for that person and that page.

On the incident, **Responders** shows how many were paged and responding, each person's answer and minutes away; **Page** pages more groups. `PAGE <group> / text` does it from the command line. A page no one has answered after five minutes is on the supervisor's exceptions; failed deliveries are on the timeline.

> Set the **address responders open** (Admin › Integrations › Paging) to the address phones reach this server at; without it pages go out with no answer link. Tested against stand-ins for Twilio, ntfy, email and a webhook; not certified by IamResponding or Active911.

CHAPTER 62

Tow rotation

In the web interface: `/admin/tows`

Police call wreckers from approved companies **in turn**. Each company tows some classes (light, medium, heavy) in some zones (Admin › Settings lists both; one zone for the whole area by default).

- **Next on rotation** on the incident (or `TOW`, `TOW heavy North`) gives the company whose last turn in that class and zone is the oldest, with its number to call, and records the call.
- Mark what they said: **Accepted**, **Declined** or **No answer** (both lose the turn; ask for the next), then **Arrived** or **Cancel**.
- An **owner's choice** or **officer's choice** of company is recorded but takes no one's turn.
- A suspended company is passed over, and the rotation screen says why each company is or is not offered.

Every request and answer is on the incident's timeline and in the ledger, so the rotation's fairness can be shown.

CHAPTER 63

Scheduled calls and special events

Work known ahead of time (the calendar button in the status bar):

- A **scheduled call** (a planned transport, an escort, a business check) becomes an incident by itself at its time, or a set number of minutes early, and sends its units if they are available (those that are not are named on the incident).
- A **special event** (a fair, a parade, a game) becomes a standby incident for its hours, and is listed as running on every console.
- Either can repeat every day, on weekdays or every week, until a last day.

Scheduled today on the situation panel lists what is coming in the next 24 hours and what is running now. An occurrence missed by more than an hour (the server was down) is not made

late; it is skipped and recorded.

CHAPTER 64

Contacts directory and on-call lists

In the web interface: `/admin/directory`

The numbers dispatch calls: utilities, agencies, the medical examiner, interpreters, public works. Each entry has numbers with labels (after hours, cell), an email, notes and tags.

- **On-call lists** say who answers tonight: shifts of directory entries by date and time, with a backup when no shift covers the time.
- An entry or list can be on the **call-out list** of call types: every incident of the type lists **To call** with the person on call now and the number (a tap calls it on a phone), and **Called** logs it on the incident. A call type's notifications (Admin › Call types › Notify) are matched to entries by name, organisation or tag.
- The directory button in the status bar (or `DIR water`) searches by name, organisation, tag or number; the situation panel shows who is on call now.

CHAPTER 65

Areas on the map (geofences)

In the web interface: `/admin/geofences`

Areas drawn on the map:

- An **alert area** tells dispatch when a unit enters or leaves it (a unit leaving the county, entering a hazard zone, arriving at a hospital): a notice on every console, the situation panel's **Area alerts**, and a line on the unit's incident. It can watch only some disciplines or units.
- A **caution area** puts its note on every incident inside it (a school zone, a firing range, a block known for trouble), on the console and the crews' terminals.

Draw a new area: click the corners on the map, then Finish. Areas show on the console map, dashed. Whether a unit is inside is worked out from its positions as they arrive, so an area drawn around a unit already there is not an arrival.

CHAPTER 66

A unit's status history

History on a unit's panel shows its day from the ledger: a bar of its statuses across the day, every status with when, how long, the incident and who changed it, its status checks, crew changes and move-ups, the incidents it worked, and the share of its known time spent on incidents. Pick another day with the date; **CSV** downloads the same.

CHAPTER 67

Patient-care reports (NEMSIS)

An EMS crew writes its patient-care report in its ePCR system; the dispatch part (when the call came in, when the unit was notified, en route, on scene, left the scene, at the hospital, back in service, where, and the dispatch reason) comes from bitdispatcher.

- **NEMSIS** on an EMS unit of the incident downloads its response as a NEMSIS 3.5 record, to import into any ePCR that takes NEMSIS files.
- With a patient-care report system set up (Admin › Integrations › Patient-care reports), **Send** posts it there, and **automatic** sends each EMS unit's response when it clears. What the system answered is on the incident.
- The dispatch reason is the call type's NEMSIS code (Admin › Call types), or suggested from its name.

> The record carries dispatch, times and the scene only; the crew completes the patient sections. It follows the NEMSIS 3.5.1 schema for those sections; tested against a stand-in, not a vendor's system.

CHAPTER 68

Warrants and papers to serve

In the web interface: `/papers`

The papers a sheriff's office or police department holds to serve: arrest and bench warrants, protective orders, evictions, summonses and subpoenas (the gavel button in the status bar). Each has the person, where to serve it, the court and number, any **caution** (armed, violent, dog), and every attempt.

- An incident near the address of an active paper (or naming its person) shows **active paper at this address** with the caution to every console and to the police crews' terminals; **Details** (police dispatch, records and supervisors) shows the papers.
- **Record the attempt**: the unit, the result (no answer, not there, moved, refused, served) and a note. Served closes it; **Recalled** and **Returned unserved** need a reason.
- Every look at the papers is recorded in the ledger.

> Confirm every warrant with the issuing agency (and NCIC where it applies) before acting on it.

CHAPTER 69

Alerting the public

Supervisors warn the public from the console: **shelter in place**, **evacuate**, police activity, a hazardous spill, a missing child, 911 being down. Press the **megaphone** in the status bar, or **Alert the public** on an incident.

Writing an alert

- **Real alert**, **Exercise** or **Test**: an exercise or test is marked as one everywhere it goes. Check this first.
- **Kind of alert**: the SAME event code (SPW shelter in place, EVI evacuation, LEW law enforcement, HMW hazardous materials, CAE child abduction, TOE 911 outage…). Choosing one fills the wording, in English and Spanish, to start from.
- **Headline**, **what is happening** and **what to do**.
- **Phone alert**: what phones show first (Wireless Emergency Alerts, 90 characters) and what text messages and push notifications say; the counter turns red past the limit. A **longer phone alert** (360) is optional.
- **Also in Spanish** adds a Spanish version; people on the lists who chose Spanish get it.
- **Where**: around the incident (a quarter mile to two miles), an area drawn on the map (Admin › Geofences), or **everyone** in the jurisdiction (its county codes).
- **Expires after** one to 24 hours.
- **Send to** the subscriber lists and the CAP systems (sirens, alert software) chosen; **keep it off some channels** asks IPAWS alert software to leave out radio and TV, weather radio, phones or public sites.

Check shows the CAP message it makes and anything wrong with it, and how many people it reaches. **Send** asks once more, with the exact phone text and area. With **two-person approval**

on, the alert waits until a second supervisor presses **Approve** (the megaphone shows *to approve*); its author can withdraw it, and the second supervisor can reject it with a reason.

In force

An alert in force shows red on the map (amber for a test) and on the megaphone, and is in the public alert feed. **Update** sends a new version to the same people that replaces it; **Cancel** sends the all-clear. Every alert, approval and delivery is in the ledger and on the incident's timeline.

> Sending to IPAWS itself (Wireless Emergency Alerts and the EAS) needs FEMA's agreement and the agency's own alert origination software; bitdispatcher writes its messages to the IPAWS profile for that software, and checks them with Google's CAP library and its IPAWS profile and with EAS Station's feed reader. No message has been sent to IPAWS.

CHAPTER 70

Public alerts: settings and lists

In the web interface: `/admin/publicalerts`

How public alerts are written and where they go (Admin › Public alerts). Administrators change the settings; supervisors keep the lists.

- **Sender**: the agency's CAP sender ID, an address it owns (alerts@county.gov), and its name.
- **Jurisdiction** and **county codes**: the six-digit SAME codes of the counties covered (0, the state's FIPS code and the county's: 051770 is Roanoke city), used for an alert to everyone and added to every alert for radio and TV.
- **Time zone**: CAP times carry the agency's offset.
- **Two-person approval** (recommended): a second supervisor approves each alert before it goes.
- **Public alert feed**: an Atom feed linking to each CAP message, and an IPAWS-style feed with the messages inside, for sirens, broadcasters' EAS encoders and apps. They show only alerts in force.
- **CAP receivers**: systems each alert is POSTed to as CAP (with a Bearer token); **Send a test** sends a test message.
- **Subscriber lists**: people who asked for alerts, reached through the paging gateways (text, email, push). A person with a place given gets only alerts whose area contains it.

Import a CSV with the columns name, phone, email, topic, lang, lat, lon. A push gateway with no one listed publishes to its own topic, a channel anyone can follow.

> The feeds are public by design: they hold only what was sent to the public.

PART 6

Setting up

Everything is set up on these screens; there is no configuration file to edit.

CHAPTER 71

Units

In the web interface: `/admin/units`

Each unit has a call sign (`E1`, `M12`, `2A31`), a type (which gives its capabilities), a station, and optionally extra capabilities, the radio's unit ID and alias (so radio emergencies and positions find it) and an agency for mutual aid. New units start out of service.

CHAPTER 72

Stations

In the web interface: `/admin/stations`

Stations are where units are based. Their positions place units with no AVL, are where move-ups post covering units, and are where drive times start from when a unit's AVL is stale. Type the address and pick it from the recorded map's suggestions: the position fills in. Or type the position.

CHAPTER 73

Receiving facilities

In the web interface: `/admin/facilities`

Receiving facilities are the hospitals and specialty centres a patient may be taken to, and whether each is taking patients. Crews and the console see the status beside a transport decision.

- **Add** a facility with an id, name and kind (hospital, trauma, burn, stroke, cardiac, psychiatric or other), its phone and position.
- **Status** is a coloured chip: open (taking patients), on diversion, or closed. A quick button changes it in one click, and the change is an attributed ledger event.

Nothing here decides a destination; it tells the people who do what is open.

CHAPTER 74

Call types and run cards

In the web interface: `/admin/calltypes`

A call type is a kind of incident (`SF` structure fire, `CHEST` chest pain) with a default priority, a discipline and a run card: how many units of each capability it needs ("3 × engine, 1 × ladder, 1 × als"). Recommendations fill the run card. Capabilities come from unit types (Admin › Settings) and units.

Critical call puts the people who work one on the supervisor's care list (chapter 50); **Send a drone** has the drone launch rule ask for a drone (chapter 47).

Auto-dispatch (priority 3 to 5 types only): when no dispatcher has sent units within the wait in Settings (60 seconds unless changed), the recommended units go by themselves, logged as *auto-dispatch*. Only a complete recommendation without warnings is sent (a verified location, every line filled); otherwise the timeline says why and a dispatcher sends it. It tries once per incident.

CHAPTER 75

Response plans

In the web interface: `/admin/plans`

A **response plan** is a run order: the units an agency wants, in due order, when a plan applies. The recommendation follows a plan's due order when one applies; if a planned unit cannot go it says why and who goes instead. A person always decides.

A plan applies when all of its conditions match the incident:

- **Call types**: the selected codes (empty means every type).
- **Modifiers**: the selected modifiers, if any.
- **First-due station area**: a station's area, or Anywhere.

- **Addresses**: the incident address starts with one of these lines (one per line), for an address-specific plan.
- **From / To**: a time of day window (HH:MM), optional.

The **due order** is the unit ids in the order they are wanted; add from the list, reorder with the up and down buttons, remove any. A plan without an order narrows nothing and is ignored.

CHAPTER 76

Recording the map

In the web interface: `/admin/map`

bitdispatcher records the OpenStreetMap data for a circle around your centre into its own store, then draws the dispatch map, routes units by road and finds addresses from that store with no internet.




Figure 5. How the recorded map is made and used

1. Choose the centre (a preset, the console map centre, or a position) and the radius (100 miles covers a county and its mutual-aid neighbours).
2. The downloads the area needs are listed at once (state extracts from Geofabrik). Press **Record**.
3. Recording takes a few minutes; dispatching carries on with the current map, which stays until the new one is complete. Each recording is a ledger event.

Bring up to date applies OpenStreetMap's daily change files (Geofabrik publishes one a day per extract) since the map was recorded: a few megabytes instead of the whole extracts, then the store is built again. Record again for a new area, or when the map is more than a year behind; downloads already made are checked against their published checksums and reused.

Aerial photos

Below the map, **Aerial photos** records photos around the same centre: full detail within the radius you choose (zoom 19: rooftops and cars) and less out to the edge (zoom 16). The estimate (tiles, size, time) follows the form; tiles already recorded are skipped, so a stopped recording carries on where it was. The sources and their terms are listed: VGIN's Virginia Base Mapping Program for Virginia, USGS The National Map (NAIP, public domain) elsewhere.

CHAPTER 77

County GIS

In the web interface: `/admin/gis`

The county's own GIS is more exact than OpenStreetMap where the county keeps it. Admin › County GIS imports its layers for the recorded map's area into a store of their own, kept when the map is recorded again.

Kind	Used for
Address points	Searched first: an exact county address point wins over OpenStreetMap's; house numbers on the map
Hydrants	Drawn with their IDs at street level
Emergency service zones, beats	Drawn and labelled on the map
Common place names	Searched
Road centrelines	Their names are searched; with address ranges (from/to, left/right) they place a number that has no point of its own, on its side of the road, and give a point on a road its number. Shown as **county range: estimate**
Overture addresses	Open address points from the Overture Maps Foundation (in the US largely the National Address Database), for any area, without a county service. Used after the county's own, marked **Overture**

1. Paste the layer's ArcGIS REST address (`…/FeatureServer/0`), choose a preset (Virginia's statewide address points and road centrelines from VGIN, or Overture's open addresses),

or upload a GeoJSON file or a CSV with latitude and longitude columns. The layer is read at once: its name, how many records lie in the area, and a guess at the kind and the fields.
2. Check the field mapping against the sample values shown beside each field, and press **Add layer**.
3. **Import now** reads every layer that is on. The store in use stays until the new one is complete; each import is a ledger event.

Search results from county data are marked as such. ArcGIS layers are read with https only, in batches, so services that cap a query still give everything.

CHAPTER 78

Settings

In the web interface: `/admin/settings`

- **Agency** name and incident number prefix.
- **Status timers**: minutes in each status before the dispatcher is prompted for a status check.
- **Mark-outs**: the kinds a unit can be marked out for (code, name, status-check minutes, which units, whether it can be pulled for a call). See Police status and mark-outs.
- **Stale** ages for AVL and caller locations.
- **Shift changes** (`07:00 19:00`) for the operations report's shift periods.
- **Travel estimates** outside the recorded map: road factor and average speed.
- **Calls**: how near and how soon callers are grouped (chapter 44); the non-emergency (chapter 45) lines, words and reply.
- **People**: the critical-call (chapter 50) words, the support line, and when to suggest a break (chapter 51).
- **Quality review** standards and the questions to listen for (Quality review (chapter 54)); **crash data** thresholds (Vehicle crash data (chapter 46)); the line-attack (chapter 56) warning level.
- **Map beyond the recorded area**: the online tile source (fetched and cached by the server, never by browsers), and the map's starting centre and zoom.
- **Unit types**: code, name, discipline, capabilities, and whether stations keep them covered (move-up suggestions).
- **Dispositions** an incident can be closed with.

Sign-in notice is the system use notice shown on the sign-in page before anyone signs in: authorised use only, use is monitored and recorded (the CJIS Security Policy asks for one). **Auto-dispatch waits** is how long a call of an auto-dispatch type waits for a dispatcher (see Call types).

CHAPTER 79

Integrations

In the web interface: `/admin/integrations`

How bitdispatcher connects to call handling and radio. Each integration shows its live state and a checklist of the hooks in use.

- **BitVoice**: its address and API token, and its certificate pinned with Read it. See BitVoice (chapter 80).
- **More BitVoice systems**: Add a BitVoice follows another one too, such as a neighbouring PSAP's: its name, address, API token, and its own EIDO token and radio secret (New makes them). Its calls show its name in the call queue, and what you do with one of them (text, rebid, video, photos) goes back to that BitVoice.
- **Neighbouring agencies**: their CADs, for sending and receiving incidents. See Incidents with neighbouring agencies (chapter 28).
- **Supplemental location (RapidSOS, NG9-1-1 LIS)**: a location server asked by HELD for where the caller's phone is: its address and the credentials the provider gives you, **Ask for every new 911 call**, and **Try a number**. The call-taker can press **Ask <name>** on the ANI / ALI panel. Not yet tested against RapidSOS itself (docs/SUPPLEMENTAL-LOCATION.md).
- **Public incident feed**: open incidents for the public or apps like PulsePoint: hundred-block addresses, points to about 100 m, no callers or notes; optional token and push address; **See what it shows** before turning it on.
- **EIDO**: the token a call-handling system uses to push EIDO to `/api/ng911/eido`.
- **Radio**: the secret for radio webhooks to `/api/radio/events`.
- **ALI spill**: the TCP address bitdispatcher listens on, and Test.
- **Hooks, drones and translation**: the hook token for transcripts, crash data, drone reports and radio words, the drone system, and the optional language model. See Hooks and connections (chapter 57).

Views (the place from every side, see Views (chapter 24)):

- **EagleView**: an application on EagleView's developer portal with Imagery API access under the agency's licence; its client ID and secret. **Sandbox** uses EagleView's test area (Omaha) to try it.
- **Panoramax**: no key; empty uses the catalogue of every instance, or give the agency's own instance.
- **Mapillary**: a client token from Mapillary's developer dashboard.
- **Google Street View link**: a link only.

- **Test at the map's centre** looks the centre up with each provider that is on and says what came back. Save first.

NERIS (fire and EMS reporting): the department's NERIS ID (FD and eight digits), a CAD integration's client ID and secret from NERIS, and the dispatch centre's name. With *Send each fire or EMS incident when it closes*, every closed incident with a fire or EMS call type or unit goes to NERIS as a CAD record (call, unit and clear times, the place, the disposition, the notes; police units left out); NERIS keeps it pending until the fire department completes it. **Check the last closed incident** asks NERIS to validate one without keeping it. Supervisors see *NERIS sent* (or why it was refused) on a closed incident, with **Send to NERIS** to send it again; a second send updates the same record. Use NERIS's test environment until NERIS has checked the integration.

CHAPTER 80

BitVoice

bitdispatcher uses every hook BitVoice offers a CAD, and needs none of them: without BitVoice, ALI and EIDO from any call-handling system work the same way.




Figure 6. Every hook BitVoice offers a CAD, and which way each runs

Hook	Way	Used for
Event stream	BitVoice → bitdispatcher	Calls ringing, answered, ended; locations; resync after a gap
EIDO	both	Incident data pushed on answer and media changes; pulled when missed
ALI spill	BitVoice → bitdispatcher	The classic location record, merged with the same call
Radio webhooks	BitVoice → bitdispatcher	Emergency button, acknowledgement, transmissions, GPS
Callbacks	bitdispatcher → BitVoice	Rebid, text to caller, video link, live video, emergency acknowledgement

Delivery failures BitVoice reports show on the Situation panel.

What a 911 call from BitVoice shows on the call (incident panel and the call-taker's ANI / ALI):

- **number verified** (or **NOT verified**) from the caller ID's STIR/SHAKEN check, with the attestation. A failed check is a reason to doubt the number, not the emergency.
- **ESInet**, the service asked for, a **CAMA** legacy trunk and how its location was looked up, and the ways text came (MSRP, SIP, RTT, TTY).
- **Address in the address data** or **NOT**, from BitVoice's LVF: missing parts, *Did they mean…* corrections, and whether the caller's position agrees with the address.
- **Location check (BitVoice)** after a rebid: which location to show first and why.
- **Caller photos and clips**: each with its SHA-256, the camera's time and GPS, shown as facts until you press **Reveal (recorded)**; every reveal is in the ledger with who looked. **Hold as evidence** keeps them past BitVoice's retention.
- Caller video opens blurred and muted; **Reveal** is recorded in BitVoice's exposure record.
- A text-to-911 call waiting for a call-taker: **Take this text**, then reply in the box.
- When a call-taker passes the call on: BitVoice's briefing for whoever takes it, and who passed it on.
- After the call: the recording's name and its summary. The briefing and the summary are both kept, each marked as written by a language model.

If BitVoice ends a call because **the caller's audio stopped** (the line went silent and no hang-up came), the call says so and the advisory panel raises it as a silent 911 call: call back.

Reports › Operations report shows BitVoice's answer times (the NENA standard: 90% within 15 seconds), who looked at callers' photos and video, and the i3 log events received. The BitVoice light in the status bar turns amber when a PSAP the ESInet routes to is full, down or unstaffed.

CHAPTER 81

Users and positions

In the web interface: `/admin/users`

Each person holds one or more **duties**: call-taker, police, fire or EMS dispatcher, dispatcher (all disciplines), supervisor, administrator, records, field crew or viewer. They choose one at sign-in (chapter 2); the rights follow it. Their role, the most they may ever do, is the least that holds all their duties:

Role	Can
Viewer	See everything, change nothing (records staff are viewers who also work records)
Field crew	The mobile terminal (chapter 32) for its own unit
Dispatcher	Work incidents, units and calls
Supervisor	Also reopen incidents, read the ledger and reports, certify reports
Administrator	Also change configuration and users

One-time codes: the list shows who has an authenticator set up; **Reset** for a lost phone. You cannot change your own duties.

Passwords are generated or at least 12 characters. Five wrong passwords lock an account for 15 minutes. The positions list shows who is signed in where.

A public demonstration account. Tick **Public demonstration account** on a viewer, dispatcher or supervisor and the sign-in page offers **Sign in as the demo user**, with a choice of its duties: one press signs a visitor in, with no password, at a position of their own (WEB- and four letters) unless they typed one. One account at most, never an administrator or a field crew, and wrong passwords typed for it do not lock the button out. Use it only on a demonstration server: anyone who can reach the server can then work as that user.

CHAPTER 82

Workstations

In the web interface: `/admin/workstations`

A **workstation** is one of the agency's console positions. A browser enrolled as a workstation signs in there, and nobody is asked which console they are at: every action is recorded with the position already known.

- **Add** a workstation with a short id (`CT1`, `DISP2`) and, if you like, a name for where it sits.
- **Duties offered** narrow what a sign-in at that position may take: Call-taker, Police, Fire or EMS dispatcher, Dispatcher (all disciplines), Supervisor, Administrator, Records. Pick none to offer every duty.
- **Enrol this browser** makes the computer you are on that workstation; it is kept here, so it is remembered next time.
- **Get a code for another computer** shows a one-time code. On the other computer, open the sign-in page, choose "Enrol this computer" and type it. It works once, for 24 hours.
- **Enrolled browsers** are listed with their label and when; revoke any that should no longer sign in there.

Every enrolment and revocation is a ledger event.

CHAPTER 83

Several sites

In the web interface: `/admin/sites`

bitdispatcher runs at two or more sites, all live at once: a main centre and a backup centre, or neighbouring counties sharing a system. There is no primary to fail over from.

- **Each site writes its own ledger** and copies the others' over https, every second, each event checked against its site's hash chain before it is kept.
- **The same picture everywhere**: every site applies all events in the same order (by time, then site), so sites that have the same events show the same state, whatever order they arrived in.
- **Cut off, a site keeps working** on its own; when the link returns the events are exchanged and both sites settle on the same state. If two sites changed the same unit meanwhile, the later change wins, at both.
- **Incident numbers** carry each site's prefix (N26-000001, S26-000001), so two sites never give the same number.
- **Setting up**: give this site a name and prefix and save; copy its token and certificate fingerprint to the other sites. Add each other site with its address, its token and its

fingerprint (**Read it** reads the certificate; check it against the one shown on that site). The status bar shows how many sites are linked.

> A site's name and prefix are written into every event it makes, so they cannot change once in use.

CHAPTER 84

Premises and hazards

In the web interface: `/admin/premises`

A premise is what the centre knows about a place before anyone calls: **hazards** to the crews (a dog, oxygen in use, an armed occupant, a Knox box), **notes** and **contacts**. It is shown with every incident within 40 m of it, on the dispatcher's incident panel and on the mobile terminal, hazards first in red. An expired premise (a temporary hazard past its date) is shown as expired.

- **Add a premise**: type the address and pick it from the suggestions (that places it), click the common hazards or type others, add notes and contacts.
- **Search** by address, name, hazard or id; click one to change or remove it.
- Supervisors and administrators change premises; everyone sees them. Each change is a ledger event.
- **Pre-plan photos and views**: on a premise, add photos (with a caption and the side they show it from) and see the views (chapter 24) of the place. A photo's SHA-256 is in the ledger: a file changed on the server is refused, not shown.

Premises from an earlier system come in through **Migration**.

CHAPTER 85

Migration from an earlier CAD

In the web interface: `/admin/migrate`

Admin › Migration brings an earlier CAD system's data over from the spreadsheets it exports, CSV or tab-separated (UTF-8 or Windows encoding).

1. **Drop the file** on the page. Its columns are matched to ours from their names, and every row is checked at once.
2. **Choose what it holds** if the guess is wrong: premises and hazards, incident history, or call types and run cards. Change any column in the table; the first row's value is shown

beside it.

3. **Import** the rows that passed. The rows that did not are listed with why (no position and an address the map does not know, a date it cannot read).

Kind	Needs	Notes
Premises and hazards	an address (or latitude and longitude)	hazards and contacts separated by ; — an address without a position is found on the map (county points, then address ranges, then the map's)
Incident history	number and date	counts as calls before at an address: the incident panel shows the last five within 40 m over ten years, and the advisory panel's repeat-address rule counts them
Call types and run cards	code and run card	"2 engine; ladder:1; als": capabilities and counts. A capability no unit type has is pointed out

Importing the same file again replaces what it brought (premises by their id, call types by their code); history is added again, so import it once. Address points go to **County GIS**, which reads CSV files with latitude and longitude as well.

CHAPTER 86

Approved guidance

In the web interface: `/admin/guidance`

Approved guidance is the agency's policies, call-taking guides, response guides and checklists. The call-taker's Resources tab shows the matching **passages** with citations; nothing is invented, only approved text is shown.

A document has an id, title, **kind** (Policy (mandatory), Guide, Prompts or Checklist), version, effective date, an optional expiry, what it supersedes, and the source where the full approved copy is. Narrow it to call types, modifiers or words, or mark it **always shown**. Only a document marked **Approved for use** is shown to call-takers.

The **text** is Markdown with `#` / `##` / `###` headings. Headings divide it into passages. Under a heading, a line like `Applies: CARD, CHEST; modifiers: WEAPONS; words: not breathing` narrows that passage.

- **Add the examples** loads clearly-titled example documents as drafts (not approved), to see how it works.

- **Try it** matches a call type, modifiers and some text and shows the passages a call-taker would see, with their title, heading, kind, version and why, or a note when nothing matches.

A document's status is a chip: approved or draft, and outdated once its expiry has passed.

CHAPTER 87

Call-taking protocols

In the web interface: `/admin/protocols`

Your agency's question sets, worked on the call-taker's Entry tab once the call is submitted (docs/PROTOCOLS.md).

- **New protocol** or **Start from the example** (marked *not for use*). Give it an ID, a name and a version, and choose the call types it is offered for.
- **Questions**: each answer leads to the next question or ends at a **determinant**. **Make first** chooses where it starts.
- **Determinants**: a code, what it means, the priority and call type it sets (or keeps), and the instructions for the caller, one per line.
- Tick **Approved for calls** when your medical director or chief has approved it; drafts are not offered. Saving checks that every answer goes somewhere and nothing loops.
- On a call: one question at a time, answers on buttons or keys 1–9; every answer is on the timeline, and the determinant shows on the dispatcher's incident.
- Protocol software you license (ProQA and others) can post its determinant to the hook instead; it shows the same way, marked with the system.

CHAPTER 88

This manual

In the web interface: `/help`

This manual is built into bitdispatcher, so it is there wherever it runs, with no internet. Every screen's Help link opens its chapter; the palette (`Ctrl K`) finds chapters by name. The same chapters are printed as docs/manual/index.html and a PDF by `make manual`.

bitdispatcher is a product of BioDream LLC, published under the Apache License 2.0. The same chapters are under **Help** in every bitdispatcher. Map data © OpenStreetMap contributors (ODbL).