

# ECE 329

## Introduction to Electromagnetic Fields

### Section E

Adapted from Prof. Cunningham's Notes

1

Goddard ECE329

Lecture 1 © 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Introduction

Professor Lynford Goddard  
2254 Micro and Nanotechnology Lab  
lgoeddard@illinois.edu  
Office hrs: TH **10-11AM**  
**Room 2254 MNTL**  
Opportunity to practice solving problems and discuss concepts



2

Goddard ECE329

Lecture 1

## Other administrative

- Course webpage:  
<https://courses.engr.illinois.edu/ece329/>
  - Syllabus
  - Course Calendar
  - Grading Policy
  - Homework assignments
  - Past Exams
  - Class Notes
  - Recorded Lectures
- Rao's book (7<sup>th</sup> ed. or 6<sup>th</sup> is good also)

3

Goddard ECE329

Lecture 1

## How to get an A in ECE329

- Time Management.** Allocate 10 hrs/wk of regularly scheduled times in the week outside of class for 329:
  - 30 min for **reading** of textbook **before** each class
  - 30 min for **studying** online notes **before** each class
  - 30 min for **studying** my notes **between** classes
  - 75 min for **practicing** problems at the tutorial session
  - 4-5 hrs/wk for HWS
    - In a semester, all lectures total only 32.5hrs, which is less than 1 week at a job! It's up to you to put in the time to learn
  - Get a 1" binder (organize lecture notes/HWs/exams)
  - Start assignments early. **Do all problems by yourself first.** If you get stuck, form study groups to work on problems together but **ALWAYS** write-up and submit **YOUR OWN** solutions. Do not blindly copy.
  - Ask questions and come to office hrs if you get stuck. Don't let confusion snowball.

4

Goddard ECE329

Lecture 1

## How to get an A in ECE329

- Practice doing problems.** Get comfortable with the math manipulations and associated physical meaning, and you will find exam problems to be easier
  - HW problems
  - Example problems worked in lecture
  - Example problems worked in online class notes
  - Old exam problems
  - Office hours
- Come to class!!**
  - HW & Class Participation = 15% of your grade**
  - I will discuss topics to be emphasized on exams and give hints about how to approach the more difficult homework problems.

5

Goddard ECE329

Lecture 1

## EM Spectrum

| Frequency           | Wavelength, $\lambda = c/f$   | Wavelength |                     |
|---------------------|---|------------|---------------------|
| 1 Hz                | $\left\{ \begin{array}{l} 1 - 300 \\ 100 - 3 \end{array} \right.$   | m          | Earth's Diameter    |
| 10 <sup>2</sup> Hz  | $\left\{ \begin{array}{l} 1 - 300 \\ 10 - 30 \end{array} \right.$   | m          | Mt Everest          |
| 10 <sup>3</sup> Hz  | $\left\{ \begin{array}{l} 100 - 300 \\ 10 - 30 \end{array} \right.$ | km         | Redwood tree        |
| 10 <sup>4</sup> Hz  | $\left\{ \begin{array}{l} 1 - 300 \\ 10 - 30 \end{array} \right.$   | m          | Person              |
| 10 <sup>5</sup> Hz  | $\left\{ \begin{array}{l} 100 - 300 \\ 100 - 3 \end{array} \right.$ | mm         | Hydrogen line       |
| 10 <sup>6</sup> Hz  | $\left\{ \begin{array}{l} 1 - 300 \\ 10 - 30 \end{array} \right.$   | μm         | O <sub>2</sub> line |
| 10 <sup>7</sup> Hz  | $\left\{ \begin{array}{l} 100 - 300 \\ 100 - 3 \end{array} \right.$ | nm         | Grain of Sand       |
| 10 <sup>8</sup> Hz  | $\left\{ \begin{array}{l} 1 - 300 \\ 10 - 30 \end{array} \right.$   | nm         | Bacteria            |
| 10 <sup>9</sup> Hz  | $\left\{ \begin{array}{l} 100 - 300 \\ 100 - 3 \end{array} \right.$ | nm         | Virus               |
| 10 <sup>10</sup> Hz | $\left\{ \begin{array}{l} 1 - 300 \\ 10 - 30 \end{array} \right.$   | nm         | Atomic spacing      |
| 10 <sup>11</sup> Hz | $\left\{ \begin{array}{l} 100 - 300 \\ 100 - 3 \end{array} \right.$ | fm         | Atom                |
| 10 <sup>12</sup> Hz | $\left\{ \begin{array}{l} 1 - 300 \\ 10 - 30 \end{array} \right.$   | fm         | Atomic Nucleus      |

6

Goddard ECE329

Lecture 1

1

## Speed of Light

### Distance Travelled

|                        |                           |
|------------------------|---------------------------|
| Across a virus         | $100 \times 10^{-18}$ sec |
| 300 meters             | 1 microsecond             |
| NY to LA               | 13 milliseconds           |
| Around earth           | 0.133 sec                 |
| <b>Earth to Moon</b>   | <b>1.2 sec</b>            |
| Earth to Sun           | 8.3 minutes               |
| Earth to Mars          | 3-21 minutes              |
| Sun to nearest star    | 4 years                   |
| Diameter of our galaxy | 100,000 years             |
| Edge of known universe | 15 billion years          |

### Travel Time

$c \equiv 299,792,458$  m/s (used to define the meter!) 7

Goddard ECE329  
Lecture 1


## Sending/Receiving EM Waves



8

Goddard ECE329  
Lecture 1

## Guiding EM Waves



9


Goddard ECE329  
Lecture 1

## Brief History of EM

Charles Coulomb in 1785 demonstrated how electric charges repel one another



Andre Marie Ampere discovered that an electric current produces a magnetic field in 1820



Michael Faraday in 1831 showed that since an electric current could produce a magnetic field, a changing magnetic field can produce an electric current. "Principle of Induction" used for first electric generators.



10

Goddard ECE329  
Lecture 1

## James Clerk Maxwell (1831-1879)

- 1855-1868 - formulates field equations for electromagnetism. Predicts existence of EM wave propagation and the speed of light. Shows theoretical possibility of generating electromagnetic radiation
- 1873: publishes *Treatise on Electricity and Magnetism*



Goddard ECE329  
Lecture 1

## Maxwell's Equations

### Integral form

$$\oint_{\text{C}} \mathbf{E} \cdot d\mathbf{L} = -\frac{d}{dt} \int_S \mathbf{B} \cdot d\mathbf{S}$$

Faraday

$$\oint_{\text{C}} \mathbf{H} \cdot d\mathbf{L} = \int_S \mathbf{J} \cdot d\mathbf{S} + \frac{d}{dt} \int_S \mathbf{D} \cdot d\mathbf{S}$$

Ampere

$$\oint_S \mathbf{D} \cdot d\mathbf{S} = \int_{\text{Vol}} \rho dv$$

Gauss

$$\oint_S \mathbf{B} \cdot d\mathbf{S} = 0$$

Gauss

### Differential Form

$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$$

$$\nabla \times \mathbf{H} = \mathbf{J} + \frac{\partial \mathbf{D}}{\partial t}$$

$$\nabla \cdot \mathbf{D} = \rho$$

$$\nabla \cdot \mathbf{B} = 0$$

**E** Electric Field  
**H** Magnetic Field  
**D**= $\epsilon_0$ **E** "Displacement Flux Density"  
**B**= $\mu_0$ **H** "Magnetic Flux Density"  
**J** Current Density  
**p** Charge Density


Goddard ECE329  
Lecture 1

12

## Computers use Differential Form for Complex Objects

From huge objects to the nanoscale,  
Maxwell's Equations always work!


VFY-218 Jet Fighter at 500 MHz



Goddard ECE329  
Lecture 1

13


## Cell Phone Interaction with Human Head



Cut plane through the cellphone  
Maps of the E-field and SAR within the cut plane.  
Relative intensities are shown in dB.

Source: Remcom Inc. website: <http://www.remcominc.com/html/index.html>

## Photonic Bandgap Defect Mode Lasers



Goddard ECE329  
Lecture 1

14

## Sections 1.1-1.2

Vector Algebra  
Cartesian Coordinates  
Differential Length Vector  
Differential Surface Vector

Adapted from Prof. Cunningham's Notes

15


Goddard ECE329  
Lecture 1

## Today's Topics

- Review
  - Scalars (numbers) and vectors
  - Unit vectors
  - Vector addition & subtraction
  - Magnitude
  - Dot product
  - Cross product
- New Topics
  - Differential length vector
  - Differential surface vector

16

## Cartesian Coordinate System



Goddard ECE329  
Lecture 1


17

## (Review at home) Vector Math

$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z \quad \vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$


### Magnitude of $\mathbf{A}$

$$|\vec{A}| = \sqrt{A_x^2 + A_y^2 + A_z^2}$$



### Unit vector in direction of $\mathbf{A}$

$$\hat{a}_A = \frac{\vec{A}}{|\vec{A}|} = \frac{A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z}{\sqrt{A_x^2 + A_y^2 + A_z^2}}$$



### Multiplication of $\mathbf{A}$ by a scalar

$$m\vec{A} = mA_x \hat{a}_x + mA_y \hat{a}_y + mA_z \hat{a}_z$$

Goddard ECE329  
Lecture 1

18


## (Review at home) Vector Math

$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$

$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$


### Addition of $\mathbf{A}$ and $\mathbf{B}$

$$\vec{A} + \vec{B} = (A_x + B_x) \hat{a}_x + (A_y + B_y) \hat{a}_y + (A_z + B_z) \hat{a}_z$$



### Subtraction of $\mathbf{A}$ and $\mathbf{B}$

$$\vec{A} - \vec{B} = (A_x - B_x) \hat{a}_x + (A_y - B_y) \hat{a}_y + (A_z - B_z) \hat{a}_z$$



19

Goddard ECE329  
Lecture 1

## Dot Product


$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$

$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$

### Dot Product of $\mathbf{A}$ and $\mathbf{B}$

$$\vec{A} \bullet \vec{B} = |\vec{A}| |\vec{B}| \cos \theta$$


Resulting quantity is a SCALAR



### Physical Meaning

(Magnitude of  $\mathbf{A}$ ) \* (Projection of  $\mathbf{B}$  onto  $\mathbf{A}$ )  
or (Magnitude of  $\mathbf{B}$ ) \* (Projection of  $\mathbf{A}$  onto  $\mathbf{B}$ )

$$\vec{A} \bullet \vec{B} = \vec{B} \bullet \vec{A}$$



20

Goddard ECE329  
Lecture 1

## Dot Product

$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$

$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$

### Dot Product of $\mathbf{A}$ and $\mathbf{B}$

$$\vec{A} \bullet \vec{B} = |\vec{A}| |\vec{B}| \cos \theta$$

$\vec{A} \perp \vec{B}$

$$\cos \theta = 0$$

$$\vec{A} \bullet \vec{B} = 0$$


$\vec{A} \parallel \vec{B}$

$$\cos \theta = 1$$

$$\vec{A} \bullet \vec{B} = |\vec{A}| |\vec{B}|$$

$$\vec{A} \perp \vec{B} \Leftrightarrow \vec{A} \bullet \vec{B} = 0$$

$$\vec{A} \parallel \vec{B} \Leftrightarrow \vec{A} \bullet \vec{B} = |\vec{A}| |\vec{B}|$$



21

Goddard ECE329  
Lecture 1

## Dot Product

$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$

$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$

$$\boxed{\vec{A} \perp \vec{B} \Leftrightarrow \vec{A} \bullet \vec{B} = 0}$$

$$\boxed{\vec{A} \parallel \vec{B} \Leftrightarrow \vec{A} \bullet \vec{B} = |\vec{A}| |\vec{B}|}$$

### Dot Product of Unit Vectors

$$\begin{array}{lll} \hat{a}_x \bullet \hat{a}_x = 1 & \hat{a}_y \bullet \hat{a}_x = 0 & \hat{a}_z \bullet \hat{a}_x = 0 \\ \hat{a}_x \bullet \hat{a}_y = 0 & \hat{a}_y \bullet \hat{a}_y = 1 & \hat{a}_z \bullet \hat{a}_y = 0 \\ \hat{a}_x \bullet \hat{a}_z = 0 & \hat{a}_y \bullet \hat{a}_z = 0 & \hat{a}_z \bullet \hat{a}_z = 1 \end{array}$$

$$\vec{A} \bullet \vec{B} = (A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z) \bullet (B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z)$$

$$\boxed{\vec{A} \bullet \vec{B} = A_x B_x + A_y B_y + A_z B_z}$$

Scalar 22

Goddard ECE329  
Lecture 1

## Discussion Problem

- Given  $\mathbf{A} = \langle 3, 2, 1 \rangle$ ,  $\mathbf{B} = \langle 1, 1, -1 \rangle$ ,  $\mathbf{C} = \langle 1, 2, 3 \rangle$ , find:
  - $|\mathbf{A} + \mathbf{B} - 4\mathbf{C}|$
  - unit vector along  $(\mathbf{A} + 2\mathbf{B} - \mathbf{C})$
  - $\mathbf{A} \cdot \mathbf{C}$

23

Goddard ECE329  
Lecture 1

Problem taken from p11 in old book

## Cross Product

$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$


$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$

### Cross Product of $\mathbf{A}$ and $\mathbf{B}$

Resulting quantity is a VECTOR

#### Magnitude

$$\vec{A} \times \vec{B} = |\vec{A}| |\vec{B}| \sin \theta$$



#### Direction

Perpendicular to BOTH  $\mathbf{A}$  and  $\mathbf{B}$

Two possible vectors satisfy this condition


Determined using the RIGHT HAND RULE

Goddard ECE329  
Lecture 1

24

## Right Hand Rule

Bus Driver in Kauai Demonstrating the Right Hand Rule



25

## Cross Product


$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$

$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$

### Cross Product of A and B

$$\vec{A} \times \vec{B} = -\vec{B} \times \vec{A}$$

Same magnitude  
Opposite direction



26

Goddard ECE329  
Lecture 1

## Cross Product

$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$

$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$

### Cross Product of A and B

$$\vec{A} \times \vec{B} = |\vec{A}| |\vec{B}| \sin \theta \hat{a}_N$$

$$\vec{A} \perp \vec{B}$$

$$\sin \theta = 1$$


$$\vec{A} \times \vec{B} = |\vec{A}| |\vec{B}| \hat{a}_N$$

$$|\vec{A}| |\vec{B}|$$

$$\sin \theta = 0$$

$$\vec{A} \times \vec{B} = 0$$

$$\vec{A} \parallel \vec{B} \Leftrightarrow \vec{A} \times \vec{B} = 0$$



27

Goddard ECE329  
Lecture 1

## Cross Product

$$\vec{A} = A_x \hat{a}_x + A_y \hat{a}_y + A_z \hat{a}_z$$

$$\vec{B} = B_x \hat{a}_x + B_y \hat{a}_y + B_z \hat{a}_z$$

$$\boxed{\vec{A} \perp \vec{B} \Leftrightarrow \vec{A} \times \vec{B} = |\vec{A}| |\vec{B}| \hat{a}_N}$$

$$\boxed{\vec{A} \parallel \vec{B} \Leftrightarrow \vec{A} \times \vec{B} = 0}$$

### Cross Product of Unit Vectors

$$\hat{a}_x \times \hat{a}_x = 0$$

$$\hat{a}_y \times \hat{a}_x = -\hat{a}_z$$

$$\hat{a}_z \times \hat{a}_x = \hat{a}_y$$

$$\hat{a}_x \times \hat{a}_y = \hat{a}_z$$


$$\hat{a}_y \times \hat{a}_y = 0$$

$$\hat{a}_z \times \hat{a}_y = -\hat{a}_x$$

$$\hat{a}_x \times \hat{a}_z = -\hat{a}_y$$

$$\hat{a}_y \times \hat{a}_z = \hat{a}_x$$

$$\hat{a}_z \times \hat{a}_z = 0$$



RH Coordinate System  
Sign Convention


$$\vec{A} \times \vec{B} = \begin{vmatrix} \hat{a}_x & \hat{a}_y & \hat{a}_z \\ A_x & A_y & A_z \\ B_x & B_y & B_z \end{vmatrix} = (A_y B_z - A_z B_y) \hat{a}_x + (A_z B_x - A_x B_z) \hat{a}_y + (A_x B_y - A_y B_x) \hat{a}_z$$

Vector  
Perpendicular to A & B  
Right Hand Rule to Select Direction

28

Goddard ECE329  
Lecture 1

## (Review at home) Vector From Origin to a Point




$$\mathbf{P}_1: (x_1, y_1, z_1)$$

Goddard ECE329  
Lecture 1

29

## (Review at home) Vector Between Two Points



$$\mathbf{P}_1: (x_1, y_1, z_1)$$


Goddard ECE329  
Lecture 1

$$\mathbf{P}_2: (x_2, y_2, z_2)$$

30

### (Review at home)

## Vector Between Two Points



$$\vec{R}_{12} = (\text{FinalPosition}) - (\text{InitialPosition})$$

$$\vec{R}_{12} = (x_2 - x_1)\hat{a}_x + (y_2 - y_1)\hat{a}_y + (z_2 - z_1)\hat{a}_z$$

31

Goddard ECE329  
Lecture 1

## Differential Length Vector

Always tangent to a curve or surface



Exact vector is different at different places on the curve or surface

What we will plug into Faraday's law


$$d\vec{l} = dx\hat{a}_x + dy\hat{a}_y + dz\hat{a}_z$$

(in cartesian coordinates only)

32

Goddard ECE329  
Lecture 1

Imagine you are walking in a river and the water pushes with a force,  $\mathbf{F}$ , determined by the river's VELOCITY VECTOR FIELD.



How much work does the river do if you walk from  $P_1$  to  $P_2$  33 along the path shown?

Goddard ECE329  
Lecture 1

## Discussion Problem

- Given  $\mathbf{A} = \langle 3, 2, 1 \rangle$ ,  $\mathbf{B} = \langle 1, 1, -1 \rangle$ ,  $\mathbf{C} = \langle 1, 2, 3 \rangle$ , find:
  - $\mathbf{B} \times \mathbf{C}$
  - $\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C})$
- For each line, find  $d\mathbf{l}$  if the z-component of  $d\mathbf{l}$  is  $dz$ :
  - $x=3, y=4$
  - $x+y=0, y+z=1$
  - the line passing from  $(2,0,0)$  thru  $(0,0,1)$

34

Goddard ECE329  
Lecture 1

Problem taken from p11 and p20 in old book

## Surface Vector

Easy example surface:  
Flat surface in the  $yz$  plane

Pick a point on the surface

Find two vectors at that point  
that are tangent to the  
surface


A surface vector is always **normal**  
(perpendicular) to the surface

You get normal vectors by performing a cross product


$$\vec{S} = \vec{l}_1 \times \vec{l}_2$$

35

Goddard ECE329  
Lecture 1



## Surface Vectors



How do we come up with a  
surface vector when a surface is  
curved?


Surface in 3D

If we zoom into a small enough  
area, the surface will "look" flat

36

Goddard ECE329  
Lecture 1

## Differential Surface Vectors



Find two differential length vectors at the point on the surface.

Think of  $d\vec{S}$  as a tiny parallelogram with sides bounded by  $d\vec{l}_1$  and  $d\vec{l}_2$  and direction perp to the surface.

$$d\vec{S} = d\vec{l}_1 \times d\vec{l}_2$$

37

Goddard ECE329  
Lecture 1

## Cartesian Coordinates

(x,y,z)

$$d\vec{l} = dx\hat{a}_x + dy\hat{a}_y + dz\hat{a}_z$$

$$d\vec{S} = \pm dydz\hat{a}_x$$


$$d\vec{S} = \pm dzdx\hat{a}_y$$

$$d\vec{S} = \pm dxdy\hat{a}_z$$

38

Goddard ECE329  
Lecture 1


## Differential area in cartesian coords



39

Goddard ECE329  
Lecture 1

## Differential surface vectors for unit vectors in cartesian coords



40

Goddard ECE329  
Lecture 1

## Lecture 1 Summary

- Dot Product  $\vec{A} \bullet \vec{B} = \underline{\hspace{2cm}} = \underline{\hspace{2cm}}$
- Cross Product

$$\vec{A} \times \vec{B} = \begin{vmatrix} \hat{a}_x & \hat{a}_y & \hat{a}_z \\ A_x & A_y & A_z \\ B_x & B_y & B_z \end{vmatrix} = \langle \underline{\hspace{1cm}}, \underline{\hspace{1cm}}, \underline{\hspace{1cm}} \rangle$$

- Next two lectures:

- Scalar and Vector Fields (1.3)
- The Lorentz Force (1.6)
- Coulomb's Law (1.4-1.6)
- Surf. Integrals/Gauss' Law (2.2,2.5)<sup>41</sup>

Goddard ECE329  
Lecture 1

## Upcoming Schedule

- Lectures 1-6 are a review of PHYS 212 and MATH 241 – covered quickly
  - Read Chapters 1 and 2 of Rao's text over the next 2 weeks
- I-clickers will be used for challenge problems beginning in Lecture 3
  - Bring them next time to test out

42

Goddard ECE329  
Lecture 1

## Lectures 2-3

### Sections 1.3-1.6, 2.2, 2.5

Scalar and Vector Fields  
 Lorentz Force Equation  
 Coulomb's Law  
 Surface Integrals  
 Connecting Coulomb's and Gauss' Law


Adapted from Prof. Cunningham's Notes

1

Goddard ECE329

Lectures 2-3

© 2007, Lyndon Goddard - Copying, publishing or distributing without express written permission is prohibited




2

Goddard ECE329

Lectures 2-3

## Vector Field




3

Goddard ECE329

Lectures 2-3

## Vector Field




4

Goddard ECE329

Lectures 2-3

## Vector Field

Example  $\vec{E}(x, y) = y\hat{a}_x + \sin x\hat{a}_y$   
 "Direction Line" or "stream line" or "flux line"




5

Goddard ECE329

Lectures 2-3

## Electric force

$$\vec{F}_E = q\vec{E}$$



6

Force vectors  $\vec{F}_E$  are parallel to  $\vec{E}$  for a positive charge  $q$


Goddard ECE329

Lectures 2-3

## Magnetic force

$$\vec{F}_M = q\vec{v} \times \vec{B}$$

Direction: Perpendicular to velocity vector – does no work!  
Perpendicular to B vector



Goddard ECE329  
Lectures 2-3

7

## Lorentz Force Equation

So if a region of space contains BOTH an **E** field and a **B** field, a moving charge will experience force from both at the same time...

$$\vec{F}_{TOTAL} = \vec{F}_E + \vec{F}_M$$

$$\vec{F}_{TOTAL} = q\vec{E} + q\vec{v} \times \vec{B}$$

8


## Application: Mass Spectrometers

### • Part I: Velocity Selector

- Particles with a specific velocity in crossed EM fields are undeflected

$$\begin{aligned}\vec{E} &= E_0 \hat{a}_z \\ \vec{B} &= -B_0 \hat{a}_y \\ \vec{v} &= v_0 \hat{a}_x \\ \vec{F}_{TOTAL} &= q(E_0 - v_0 B_0) \hat{a}_z = 0 \text{ iff } v_0 = E_0 / B_0\end{aligned}$$

Goddard ECE329  
Lectures 2-3



9

## Application: Mass Spectrometers

### • Part II: Mass Selector

- Mass sets the radius of B-field orbit since particle velocity is the same

$$\begin{aligned}\vec{B} &= B_0 \hat{a}_z \\ \vec{v} &= v_0 \hat{a}_x \\ F_c &= mv_0^2/R = qv_0 B_0\end{aligned}$$

Goddard ECE329  
Lectures 2-3

10

Problem: Solve for R as a function of the particle's mass, m, and velocity,  $v_0$

$$F_c = mv_0^2/R = qv_0 B_0$$

## Current = Moving Charge

What is CURRENT? CHARGES IN MOTION!!

$$\underline{\underline{I d\vec{l}}} \quad I d\vec{l} = q \vec{v}$$

$$\frac{\text{coul}}{\text{sec}} \cdot m = \text{coul} \cdot \frac{m}{\text{sec}}$$

So the current in a wire,  $I$ , flowing across a magnetic field will feel a force...


11

Goddard ECE329  
Lectures 2-3

## Magnetic force

$$F_M = (I d\vec{l}) \times \vec{B} = q \vec{v} \times \vec{B}$$

Direction: Perpendicular to velocity vector  
Perpendicular to B vector



Goddard ECE329  
Lectures 2-3

12

## Electrostatic Force

What is the force  $F_2$  on a point charge  $Q_2$  due to a single point charge  $Q_1$  located a distance  $R$  away?



13

Goddard ECE329  
Lectures 2-3

## Coulomb's observations

- The magnitude of  $F$  is
  - proportional to the product of the charges
  - inversely proportional to the square of the distance
  - depends on the medium
- $F$  points along the joining line
- Like charges repel; unlike charges attract

14

Goddard ECE329  
Lectures 2-3

## Coulomb's Law



$$\vec{F}_1 = \frac{Q_1 Q_2}{4\pi\epsilon_0 R^2} \hat{a}_{21}$$

15

Goddard ECE329  
Lectures 2-3

## Electric Field

- The electric field  $\mathbf{E}$  is the force per unit charge caused by the source charges

Tiny "test charge"  
(with + charge)




$$\vec{E} = \lim_{Q_2 \rightarrow 0} \frac{\vec{F}_2}{Q_2} = \frac{Q_1}{4\pi\epsilon_0 R^2} \hat{a}_R$$

16

Goddard ECE329  
Lectures 2-3


## Electric Field Around a Point Charge



17

Goddard ECE329  
Lectures 2-3

## Surfaces of Constant E Magnitude are Spheres



18

Goddard ECE329  
Lectures 2-3


## Field Lines

- Another way to graphically represent vector fields
- The field strength is proportional to the **density** of field lines
- E-field lines begin on + charges, initially emanating uniformly in all directions, and end on - charges
  - Can't stop in midair but can extend to  $\infty$
- They **never** intersect

19

Goddard ECE329  
Lectures 2-3


## Electric Field Around a Point Charge



20

Goddard ECE329  
Lectures 2-3

## Electric Field Around a Point Charge



$$\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_R$$

Gauss' Law  
Number of  
field lines  
passing thru  
any surface  
that encloses  
 $Q_1$  is constant

21

Goddard ECE329  
Lectures 2-3

## Calculating the Electric Field

Point Charge at position  $(x_1, y_1, z_1)$

Position where we want to calculate electric field at Position  $(x_2, y_2, z_2)$

$$R = \sqrt{(x_2 - x_1)^2 + (y_2 - y_1)^2 + (z_2 - z_1)^2}$$


$$\hat{a}_R = \frac{(x_2 - x_1)\hat{a}_x + (y_2 - y_1)\hat{a}_y + (z_2 - z_1)\hat{a}_z}{R}$$

Unit vector pointing along direction from Q to Point

22

Goddard ECE329  
Lectures 2-3


## Superposition of E Fields



23

Goddard ECE329  
Lectures 2-3

## Example: Calculate the E-field of a Dipole at a Point




Tip: We only need to work in 2D. Why?

24

Goddard ECE329  
Lectures 2-3

## Example: E of Dipole




Tip: Use symmetry to eliminate components that cancel. Here, we only need to calculate the y-component and only for one of the charges (let's say for +Q). Why?

25

Goddard ECE329  
Lectures 2-3

## Example: E of Dipole




$$\vec{E}_{TOT} = \vec{E}_1 + \vec{E}_2 = 2E_{1y}\hat{a}_y$$

26

Goddard ECE329  
Lectures 2-3

## Example: E of Dipole




$$\vec{R}_{from +Q to P} = \langle x_2 - x_1, y_2 - y_1 \rangle = \langle D, -a/2 \rangle$$

$$\hat{a}_R = \frac{\langle D, -a/2 \rangle}{\sqrt{D^2 + a^2/4}} \quad \vec{E}_1 = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_R$$

27

Goddard ECE329  
Lectures 2-3

## Example: E of Dipole



$$E_{1y} = \left( \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_y \right) \bullet \hat{a}_y$$

$$\vec{E}_{TOT} = 2 \cdot \frac{Q}{4\pi\epsilon_0 R^2} \left( \frac{-a/2}{R} \right) \hat{a}_y$$

UNITS  
(Newtons per  
Coulomb)

28

Goddard ECE329  
Lectures 2-3

## Patented 5-Step Program for Problem Solving

1. MAKE A **LARGE CLEAR DRAWING**
  - a. Also draw cross-sections if the problem is in 3D
  - b. Pick a coordinate system that is appropriate for the symmetry of the problem
2. Divide charge distributions into tiny pieces
3. Find  $d\vec{E}$  of one tiny piece
4. Use SYMMETRY to eliminate any components that cancel (i.e. add to ZERO)
5. INTEGRATE to add contribution of ALL the tiny pieces

29

Goddard ECE329  
Lectures 2-3

## Example Charge Distributions

- Several discrete points of charge
- Line of charge
- Ring of charge
- Nonuniform lines or rings of charge
- An infinite sheet of charge
- Infinite box of charge
- Spherical surface of charge
- Cylindrical surface of charge
- Spherical volume of charge
- Cylindrical volume of charge


30

Goddard ECE329  
Lectures 2-3

### (Review at home)

#### Example 1: Find Total Charge of a Linear Charge Distribution

Linear Charge  $\lambda_0$  (C/m) distribution in a circular loop of radius =  $a$



One little piece has a charge (in coulombs)  
 $dQ = (\lambda_0)(ad\phi)$


Goddard ECE329  
Lectures 2-3

31

### (Review at home)

#### Example 1: Find Total Charge of a Linear Charge Distribution

Linear Charge  $\lambda_0$  (C/m) distribution in a circular loop of radius =  $a$



One little piece has a charge (in coulombs)  
 $dQ = (\lambda_0)(ad\phi)$

Integrate to get the entire charge of the loop:

$$Q = \int_{\phi=0}^{2\pi} (\lambda_0)(ad\phi) = 2\pi\lambda_0 a$$

Units:  
Coulombs

Goddard ECE329  
Lectures 2-3

32

### (Review at home)

#### Example 2: F due to line of charge



Rod has a TOTAL charge =  $Q$  (coul)

So the rod has a charge DENSITY  $\rho_l = Q/L$  (coul/m)


Find the FORCE exerted by the whole charged rod on the charge  $q$

Goddard ECE329  
Lectures 2-3

33

### (Review at home)

#### Example 2: F due to line of charge



What is the small amount of force,  $dF$ , applied by a small sliver of the rod?

Differential force applied to  $q$

$$d\vec{F} = \frac{[Q dx]}{4\pi\epsilon_0 R^2} q \hat{a}_x$$


Differential charge in one small sliver (coul)

$$R = (L + a) - x$$

34

### (Review at home)

#### Example 2: F due to line of charge



INTEGRATE the force from each part of the rod to obtain the force due to the whole thing:

$$\vec{F} = \int_0^L \frac{qQ}{4\pi\epsilon_0 L} \frac{dx}{(L+a-x)^2} \hat{a}_x$$


Fortunately,  $\hat{a}_x$  is constant and can be taken outside of the integral. Not so simple in cylindrical/spherical coordinates!

Goddard ECE329  
Lectures 2-3

35

### (Review at home)

#### Example 2: F due to line of charge



INTEGRATE the force from each part of the rod to obtain the force due to the whole thing:

$$\vec{F} = \frac{qQ}{4\pi\epsilon_0 L} \hat{a}_x \int_0^L \frac{dx}{(L+a-x)^2} = \frac{qQ}{4\pi\epsilon_0 L} \hat{a}_x \left[ \frac{1}{L+a-x} \right]_0^L$$


$$\vec{F} = \frac{qQ}{4\pi\epsilon_0 L} \hat{a}_x \left[ \frac{1}{a} - \frac{1}{L+a} \right] = \frac{qQ}{4\pi\epsilon_0 a(L+a)} \hat{a}_x$$

Goddard ECE329  
Lectures 2-3

36

Units: N

### Example 3: $\mathbf{E}$ due to line of charge



Linear charge distribution  $\rho_l$  (coul/m) from  $-a < z < a$


Find  $\mathbf{E}$  at point on  $xy$  plane

Next, consider what happens when the line is infinitely long

37

Goddard ECE329  
Lectures 2-3

### Example 3: $\mathbf{E}$ due to line of charge




Cylindrical symmetry so use cylindrical coordinates  $(r, \phi, z)$   
 $\mathbf{E}_{\text{total}}$  will point in  $\hat{a}_r$  direction, why?

Goddard ECE329  
Lectures 2-3

38

### Example 3: $\mathbf{E}$ due to line of charge



$$\overrightarrow{dE} = \frac{dQ}{4\pi\epsilon_0 R^2} \hat{a}_R$$

$$dE_r = dE \cos(\alpha) = dE \frac{r}{R}$$

$$R = \sqrt{r^2 + z^2}$$

$$E_r = \frac{\rho_l}{4\pi\epsilon_0} \int_{z=-a}^a \frac{r}{(r^2 + z^2)^{3/2}} dz (\hat{a}_r)$$

Slightly difficult to integrate directly

39

Goddard ECE329  
Lectures 2-3

### Example 3: $\mathbf{E}$ due to line of charge

$$E_r = \frac{\rho_l}{4\pi\epsilon_0} \int_{z=-a}^a \frac{r}{(r^2 + z^2)^{3/2}} dz (\hat{a}_r)$$

$$R = \frac{r}{\cos(\alpha)}, \quad z = r \tan(\alpha), \quad dz = r \sec^2(\alpha) d\alpha$$

$$E_r = \frac{\rho_l}{4\pi\epsilon_0} \int_{z=-a}^a r \frac{\cos^3(\alpha)}{r^3} (r \sec^2(\alpha) d\alpha) (\hat{a}_r)$$


$$= \frac{\rho_l}{4\pi\epsilon_0 r} (\hat{a}_r) \int_{\tan(\alpha)=-a/r}^{\tan(\alpha)=+a/r} \cos(\alpha) d\alpha = \frac{\rho_l}{4\pi\epsilon_0 r} (\hat{a}_r) \sin(\alpha)$$

$$= \frac{\rho_l}{4\pi\epsilon_0 r} (\hat{a}_r) 2 \frac{a}{\sqrt{a^2 + r^2}}$$

40

Goddard ECE329  
Lectures 2-3

### Example 4: $\mathbf{E}$ due to $\infty$ line of charge



$a \gg r$  so we get

$$\lim_{a \rightarrow \infty} E_r = \frac{\rho_l}{4\pi\epsilon_0 r} (\hat{a}_r) 2 \lim_{a \rightarrow \infty} \frac{a}{\sqrt{a^2 + r^2}} \\ = \frac{\rho_l}{2\pi\epsilon_0 r} (\hat{a}_r)$$

$$E_r = \frac{\rho_l}{2\pi\epsilon_0 r} (\hat{a}_r)$$

Field strength now drops off as  $1/r$ ,  
 Not as  $1/r^2$  like a point charge

41

Goddard ECE329  
Lectures 2-3

### Lecture 2 Summary

- The electric field  $\mathbf{E}$  is the \_\_\_\_\_ per \_\_\_\_\_ caused by the source charges. It points along the \_\_\_\_\_ line. For a point charge,

$$\mathbf{E} =$$

- Next class:  
 Surface Integrals (2.2)  
 Connecting Coulomb's and Gauss' Law (2.5)

42

Goddard ECE329  
Lectures 2-3

## Lecture 3 Sections 2.2, 2.5

### Surface Integrals Connecting Coulomb's and Gauss' Law

Adapted from Prof. Cunningham's Notes


Goddard ECE329  
Lectures 2-3

43

## Electric Field Around a Point Charge

$$\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_R$$

Gauss' Law  
Number of  
field lines  
passing thru  
**any** surface  
that encloses  
 $Q_1$  is constant




Goddard ECE329  
Lectures 2-3

44

## Surface Integrals

- Flux = # of arrows that pass thru a surface; it depends on:

- The density of vectors



- The angle of the surface





- The area of the surface



Goddard ECE329  
Lectures 2-3

45

## Surface Integral describes the Flux of a Vector Field



$$\begin{aligned} \text{Flux} &= \vec{B} \bullet \Delta \vec{S} \\ &= (\vec{B} \bullet \hat{a}_n) |\Delta S| \\ &= (B \cos \alpha) |\Delta S| \\ &= |B_n| |\Delta S| \end{aligned}$$


Goddard ECE329  
Lectures 2-3

46

## Trick that works sometimes

If the flux is

- Uniform (has equal magnitude across whole surface)
- Perpendicular to the surface




$$\psi = \iint_S \vec{B} \bullet d\vec{S} = B \cdot A$$

47

Goddard ECE329  
Lectures 2-3

## In the general case ...



$$\begin{aligned} \text{Flux} &= \sum_{j=1}^n \Delta \psi_j \\ &= \sum_{j=1}^n \mathbf{B}_j \bullet \Delta \mathbf{S}_j \end{aligned}$$

In the limit  $n \rightarrow \infty$ ,


$$\text{Flux, } \psi = \int_S \mathbf{B} \bullet d\mathbf{S}$$

= Surface integral of B over S.

Goddard ECE329  
Lectures 2-3

48

## Differential surface vectors for unit vectors in cartesian coords




Goddard ECE  
Lectures 2-3

49

## Electric Flux = Charge Enclosed

- Coulomb's Law for the Electric field of a point charge:  $\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{r}_R$



Define  $\mathbf{D} = \epsilon_0 \mathbf{E}$  to be the "displacement flux density"


$$\begin{aligned}\psi_E &= \iint_S \vec{D} \cdot d\vec{S} = \iint_S \epsilon_0 \vec{E} \cdot d\vec{S} \\ &= \epsilon_0 E (\text{Surf Area}) \\ &= \epsilon_0 \frac{Q}{4\pi\epsilon_0 R^2} (4\pi R^2) = Q\end{aligned}$$

50

Goddard ECE329  
Lectures 2-3

## Same Flux Out of Any Surface

- Same # of field lines pass thru any surface that encloses Q



$$\psi_E = \iint_S \vec{D} \cdot d\vec{S} = Q_{\text{enclosed}}$$


Goddard ECE329  
Lectures 2-3

Our first Maxwell Equation!

51

## Superposition

- The flux for an arbitrary distribution of charges is obtained using superposition



52

Goddard ECE329  
Lectures 2-3

## Simple Example 1

6-sided cube with Q at the center:



Flux out of entire box = Q  
Flux out of one side = Q/6


What if Q is not at the center?

Goddard ECE329  
Lectures 2-3

53

## Simple Example 2

Flux out of hemisphere with Q at the center = Q/2




Goddard ECE329  
Lectures 2-3

54

## Challenge Question 1

- What is the flux across the xy plane  $\mathbf{a}_n = \mathbf{a}_z$  for a dipole:  $+Q$  at  $(0,0,a/2)$  and  $-Q$  at  $(0,0,-a/2)$ ?

- (a)  $Q/2$   
 (b)  $-Q/2$   
 (c)  $-Q$   
 (d)  $-3Q/2$   
 (e)  $-2Q$




55

Goddard ECE329  
Lectures 2-3

## Challenge Question 2

- What is the flux across the xy plane  $\mathbf{a}_n = \mathbf{a}_z$  for the charge distribution:  $+2Q$  at  $(0,0,a/2)$  and  $-Q$  at  $(0,0,-a/2)$ ? (Hint: Use superposition.)


- (a)  $Q/2$   
 (b)  $-Q/2$   
 (c)  $-Q$   
 (d)  $-3Q/2$   
 (e)  $-2Q$



56

Goddard ECE329  
Lectures 2-3


## Example 3: $\mathbf{E}$ due to $\infty$ line of charge



57

Goddard ECE329  
Lectures 2-3


## Example 3: $\mathbf{E}$ due to $\infty$ line of charge



58

Goddard ECE329  
Lectures 2-3

## Example 4: $\mathbf{E}$ due to a surface of charge



59

Goddard ECE329  
Lectures 2-3

## The (Fictional) Yadraf Bug: Flux and Surface Integrals


- The Yadraf Bug
  - They live in the ground
  - They only come out at night to search for food
  - Very hard to see - REALLY small
  - After gathering food, they always return to their hole in the ground



60

Goddard ECE329  
Lectures 2-3


## Yadaraf Bug Travel Paths



61

Goddard ECE329  
Lectures 2-3


## Yadaraf Bug Travel Paths



62

Goddard ECE329  
Lectures 2-3

## Yadaraf Bug Counter




- Register a +1 count for each bug going through in one direction
- Register a -1 count for each bug going through in the opposite direction
- Has a known area for the bugs to pass through

63

Goddard ECE329  
Lectures 2-3

## Yadaraf Bug Travel Paths



64

Goddard ECE329  
Lectures 2-3

## Bug Counting Net

Bug Density  
Vectors  
(Bugs/m<sup>2</sup>)

$\vec{B}$

$dx$   
 $dy$   
 $d\vec{S}$   
(normal to net section)

65

Goddard ECE329  
Lectures 2-3

## "Closed" Bug Counting Net

Bug Density  
Vectors  
(Bugs/m<sup>2</sup>)


$\vec{B}$

$dx$   
 $dy$   
 $d\vec{S}$   
(normal to net section)

66

Goddard ECE329  
Lectures 2-3

So magnetic flux,  $\psi_B$ , through a CLOSED surface is always zero



67

Goddard ECE329  
Lectures 2-3

Magnetic field lines form closed paths (they do not begin or end)

## Gauss' Law for B Fields

Net flux of magnetic field lines through any closed surface MUST be zero.

$$\iint_S \vec{B} \bullet d\vec{S} = 0$$

Our Second Maxwell Equation!

68

Goddard ECE329  
Lectures 2-3

## Lecture 3 Summary

- Gauss' Law

$$\psi_E = \iint_S \vec{D} \bullet d\vec{S} = Q_{enclosed}$$

FLUX OUT = CHARGE ENCLOSED

$$\iint_S \vec{B} \bullet d\vec{S} = 0$$

MAGNETIC FLUX LINES DO NOT BEGIN/END

69

Goddard ECE329  
Lectures 2-3

## Lectures 4-5 Sections 3.1-3.3

Review of Vector Calculus  
Curl and Divergence  
Maxwell's Equations in Differential Form

Adapted from Prof. Cunningham's Notes

1

Goddard ECE329  
Lectures 4-5

© 2007, Lyndon Goddard - Copying, publishing or distributing without express written permission is prohibited

## Fundamental Theorem of Single Variable Calculus

$$\int_a^b f'(x)dx = f(b) - f(a)$$

$df = f'(x)dx$  is the infinitesimal change of  $f$  in going from  $x$  to  $x+dx$

Thus, chopping up the interval  $(a,b)$  into pieces  $dx$  and adding up  $df$  gives the total change

2

Goddard ECE329  
Lectures 4-5

## Fundamental Theorem of Multi-Variable Calculus

$$\int_a^b \nabla f \bullet d\vec{l} = f(b) - f(a)$$

$$\nabla f = \frac{\partial f}{\partial x} \hat{a}_x + \frac{\partial f}{\partial y} \hat{a}_y + \frac{\partial f}{\partial z} \hat{a}_z$$

$df = \nabla f \cdot dl$  is the infinitesimal change of  $f$  in going from  $(x,y,z)$  to  $(x+dx, y+dy, z+dz)$

Thus, chopping up the path  $(a,b)$  into pieces  $dl$  and adding up  $df$  gives the total change

3

Goddard ECE329  
Lectures 4-5

## $\nabla f$ is a conservative field

$$\int_a^b \nabla f \bullet d\vec{l} = f(b) - f(a)$$

$$\nabla f = \frac{\partial f}{\partial x} \hat{a}_x + \frac{\partial f}{\partial y} \hat{a}_y + \frac{\partial f}{\partial z} \hat{a}_z$$

The right hand side doesn't depend on path so  
 $\nabla f$  is conservative


$$\oint_C \nabla f \bullet d\vec{l} = 0$$

$\nabla f$  is curl-free

4

Goddard ECE329  
Lectures 4-5

## Curl



$$\nabla \times \vec{v} = \begin{vmatrix} \hat{a}_x & \hat{a}_y & \hat{a}_z \\ \frac{\partial}{\partial x} & \frac{\partial}{\partial y} & \frac{\partial}{\partial z} \\ v_x & v_y & v_z \end{vmatrix} = 5\hat{a}_z$$

$\nabla \times \vec{v}$  is a measure of how much the vector field  $\vec{v}$  circulates at a given point


A place of high curl is like a whirlpool

- Everywhere here is a whirlpool of strength 5

5

Goddard ECE329  
Lectures 4-5


## Physical Interpretation of Curl



6

Goddard ECE329  
Lectures 4-5

## Physical Interpretation of Curl



Goddard ECE329  
Lectures 4-5

7


## Meaning of Curl

- The curl meter only spins if there is a non-uniformity in the vector field in a direction **perpendicular** to the field
  - Curl describes variation ACROSS the flow of the field
- Rotation rate is proportional to the degree of non-uniformity
- Rotation is described with a magnitude and a direction – so it's a **VECTOR** and it's given by the right hand rule

8

Goddard ECE329  
Lectures 4-5

## Curl



Goddard ECE329  
Lectures 4-5

9

## Example: Curl

- Find the curl of  $\mathbf{A} = (x^2 - 4)\mathbf{a}_y$

10

Goddard ECE329  
Lectures 4-5

From D3.7 (p 159) of old book

## Stokes' Theorem

$$\oint_C \vec{v} \bullet d\vec{l} = \sum_{C_i} \oint \vec{v} \bullet d\vec{l} = \sum_i \iint_S (\nabla \times \vec{v}) \bullet d\vec{S} = \iint_S (\nabla \times \vec{v}) \bullet d\vec{S}$$



$\nabla \times \mathbf{v}$  is a measure of how much the vector field  $\mathbf{v}$  circulates at a given point


A place of high curl is like a whirlpool

Thus, adding up the circulation from each whirlpool inside a region = the total circ. along the boundary

11

Goddard ECE329  
Lectures 4-5

## Optional: Derivation of Stokes' Theorem



$$\begin{aligned} \oint_C \vec{v} \bullet d\vec{l} &= [v_y(x+dx, y+dy/2) - v_y(x, y+dy/2)] \cdot dy \\ &\quad - [v_x(x+dx/2, y+dy) - v_x(x+dx/2, y)] \cdot dx \\ &= \left( \frac{dv_y}{dx} - \frac{dv_x}{dy} \right)_{x+dx/2, y+dy/2} \cdot dx \cdot dy \end{aligned}$$

$$\oint_C \vec{v} \bullet d\vec{l} = (\nabla \times \vec{v}) \bullet d\vec{S} \approx \iint_S (\nabla \times \vec{v}) \bullet d\vec{S}$$

12

Goddard ECE329  
Lectures 4-5

$\mathbf{v}$  is a conservative field  
iff  $\nabla \times \mathbf{v} = 0$

$$\oint_C \vec{v} \bullet d\vec{l} = 0 = \iint_S (\nabla \times \vec{v}) \bullet d\vec{S}$$

The following are therefore equivalent:

$\mathbf{v}$  is conservative     $\mathbf{v}$  is curl-free

$$\oint_C \vec{v} \bullet d\vec{l} = 0 \quad \int_a^b \vec{v} \bullet d\vec{l} \text{ is path independent}$$


$$\vec{v} = -\nabla f \text{ for some scalar potential } f$$

Goddard ECE329  
Lectures 4-5


13

## Curl at a Point

"E has CURL" means  $EMF \neq 0$  around a tiny closed path at a particular point – line integral is path dependent



If there is any DIFFERENCE in  $E_y$  in the x direction  $\frac{dE_y}{dx} \neq 0$   
Path 123  $\neq$  Path 143



Or if there is any DIFFERENCE in  $E_x$  in the y direction  $\frac{dE_x}{dy} \neq 0$   
Path 123  $\neq$  Path 143

14

## Maxwell's Equations in Differential Form

Faraday's Law  $\oint_C \vec{E} \bullet d\vec{l} = -\frac{d}{dt} \iint_S \vec{B} \bullet d\vec{S}$

Stokes' Thm

$$\oint_C \vec{E} \bullet d\vec{l} = \iint_S (\nabla \times \vec{E}) \bullet d\vec{S} = -\frac{d}{dt} \iint_S \vec{B} \bullet d\vec{S}$$

$$\Rightarrow \nabla \times \vec{E} = -\frac{d\vec{B}}{dt}$$

Goddard ECE329  
Lectures 4-5

15


## Faraday's Law In Differential Form

$$\nabla \times \vec{E} = -\frac{d\vec{B}}{dt}$$

16

## Challenge Question

- For  $\mathbf{E} = E_0 \cos(\omega t - \beta z) \mathbf{a}_x$ , which direction will  $d\mathbf{B}/dt$  point at  $t=0, z=\pi/(4\beta)$ ?



- (a)  $\mathbf{a}_x$ , (b)  $\mathbf{a}_y$ , (c)  $-\mathbf{a}_y$ , (d)  $\mathbf{a}_z$ , (e)  $d\mathbf{B}/dt=0$

- Hint: find  $d\mathbf{B}/dt$  directly or use the sketch

Goddard ECE329  
Lectures 4-5

From D3.1 (p 141) of old book

17

## Maxwell's Equations in Differential Form

Ampere's Law  $\oint_C \vec{H} \bullet d\vec{l} = \iint_S \vec{J} \bullet d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \bullet d\vec{S}$

Stokes' Thm


$$\oint_C \vec{H} \bullet d\vec{l} = \iint_S (\nabla \times \vec{H}) \bullet d\vec{S} = \iint_S (\vec{J} + \frac{d\vec{D}}{dt}) \bullet d\vec{S}$$

$$\Rightarrow \nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$$

Goddard ECE329  
Lectures 4-5

18

## Ampere's Law In Differential Form



$$MMF = \oint \vec{H} \cdot d\vec{l} \neq 0$$

If there is any current going through a particular point

$H$  has "CURL" at a point if there is current going through the point:




CONDUCTION current  
DISPLACEMENT current

19

Goddard ECE329  
Lectures 4-5

## Divergence

$$\vec{v} = <3x, 2y, 0>$$



$$\nabla \cdot \vec{v} = \frac{\partial v_x}{\partial x} + \frac{\partial v_y}{\partial y} + \frac{\partial v_z}{\partial z} = 5$$


$\nabla \cdot \vec{v}$  is a measure of how many field lines for  $\vec{v}$  are created at a given point  
A place of high divergence is like a water faucet

— Everywhere here is a faucet of strength 5


20

Goddard ECE329  
Lectures 4-5


## Meaning of Divergence



Flux in = flux out  
so no sources or sinks inside V.



Flux out > flux in  
Positive divergence.  
Must be a source  
inside V.



Flux out < flux in  
Negative divergence.  
Must be a sink or drain  
inside V.

21

Goddard ECE329  
Lectures 4-5


## Meaning of Divergence

- There is divergence if there is a non-uniformity in the vector field in a direction **parallel** to the field
  - Divergence describes variation ALONG the flow of the field
- Divergence is proportional to the degree of non-uniformity
- Divergence is described only by the magnitude – so it's a SCALAR

22

Goddard ECE329  
Lectures 4-5

## Divergence



Goddard ECE329  
Lectures 4-5

## Example: Divergence


- Find the divergence of  $\mathbf{A} = (x-2)^2 \mathbf{a}_x$

Goddard ECE329  
Lectures 4-5

From D3.8 (p 159) of old book

24

## Divergence Theorem



$$\iiint_V \nabla \cdot \vec{v} dV = \oint_{\partial V} \vec{v} \cdot d\vec{S}$$


$\nabla \cdot \vec{v}$  is a measure of how many field lines for  $\vec{v}$  are created at a given point

Thus, adding up the net # lines created inside a volume = the flux of lines out its boundary

25

Goddard ECE329  
Lectures 4-5

## Optional: Derivation of Divergence Theorem



$$\begin{aligned} \iint_{\partial V} \vec{v} \cdot d\vec{S} &= [v_x(x+dx) - v_x(x)] \cdot dy \cdot dz \\ &\quad + [v_y(y+dy) - v_y(y)] \cdot dx \cdot dz \\ &\quad + [v_z(z+dz) - v_z(z)] \cdot dx \cdot dy \end{aligned}$$

$$\iint_{\partial V} \vec{v} \cdot d\vec{S} = (\vec{\nabla} \cdot \vec{v}) dV \approx \iiint_V (\vec{\nabla} \cdot \vec{v}) dV$$

26

Goddard ECE329  
Lectures 4-5

## Maxwell's Equations in Differential Form

Gauss' Law

$$\iint_S \vec{B} \cdot d\vec{S} = 0$$

Divergence Thm

$$\iint_S \vec{B} \cdot d\vec{S} = \iiint_V \nabla \cdot \vec{B} dV = 0$$

$$\Rightarrow \nabla \cdot \vec{B} = 0$$

27

Goddard ECE329  
Lectures 4-5

## Does $\mathbf{B}$ satisfy $\nabla \cdot \mathbf{B} = 0$

$$\vec{B} = \frac{\mu_0 I}{2\pi r} \hat{a}_\phi$$

28

Goddard ECE329  
Lectures 4-5

## Maxwell's Equations in Differential Form

Gauss' Law

$$\iint_S \vec{D} \cdot d\vec{S} = \iiint_V \rho dV$$

Divergence Thm

$$\iint_S \vec{D} \cdot d\vec{S} = \iiint_V \nabla \cdot \vec{D} dV = \iiint_V \rho dV$$

$$\Rightarrow \nabla \cdot \vec{D} = \rho$$

29

Goddard ECE329  
Lectures 4-5


## E-field of pn junction (ECE 340)

p-type: holes are the free charge carriers

n-type: electrons are the free charge carriers

Hole Acceptor Ion Electron Donor Ion

An acceptor is a dopant atom that when added to a semiconductor can form a p-type region, e.g. Boron (group III) is an acceptor for Silicon (group IV)



A donor is a dopant atom that when added to a semiconductor can form an n-type region, e.g. Phosphorus (group V) is a donor for Silicon (group IV)

- Find the E-field for an evenly doped:  $N_d = N_a$  pn junction:  $\rho = \begin{cases} -\rho_0 = -qN_a & \text{for } -a < x < 0, \\ qN_d & \text{for } 0 < x < a, \\ 0 & \text{for } |x| > a \end{cases}$

Goddard ECE329  
Lectures 4-5

From Example 3.5 (p 145) of old book

30

## Blank space for work

31

Goddard ECE329  
Lectures 4-5

## Challenge Question

- Can  $\mathbf{A} = y\mathbf{a}_x + x\mathbf{a}_y$  be an E or B field in a region of free space where  $J=0$ ,  $\rho=0$ , and electrostatics applies? Workspace:

- Yes, but  $\mathbf{A}$  can only be an E-field
- Yes, but  $\mathbf{A}$  can only be a B-field
- Yes,  $\mathbf{A}$  can be either an E or B field
- No,  $\mathbf{A}$  cannot be either an E or B field

32

Goddard ECE329  
Lectures 4-5

From Problem 3.11a (p 198) of old book

## Continuity Equation in Differential Form

$$\text{Continuity Eqn} \quad \iint_S \vec{J} \bullet d\vec{S} = -\frac{d}{dt} \iiint_V \rho dV$$

Divergence Thm

$$\begin{aligned} \iint_S \vec{J} \bullet d\vec{S} &= \iiint_V \nabla \bullet \vec{J} dV = -\frac{d}{dt} \iiint_V \rho dV \\ \Rightarrow \nabla \bullet \vec{J} &= -\frac{d\rho}{dt} \end{aligned}$$

33

Goddard ECE329  
Lectures 4-5

## Useful Relationships

$$\nabla \bullet (\nabla \times \vec{A}) = 0$$

$\nabla \times (\nabla f) = 0$  We already knew  $\nabla f$  is conservative

$$\nabla \times (\nabla \times \vec{A}) = \nabla(\nabla \bullet \vec{A}) - \nabla^2 \vec{A} \text{ Must use cartesian coordinates!}$$

$$\nabla^2 \vec{A} \equiv (\nabla^2 A_x) \hat{a}_x + (\nabla^2 A_y) \hat{a}_y + (\nabla^2 A_z) \hat{a}_z$$

$$0 = \nabla \bullet (\nabla \times \vec{H}) = \nabla \bullet (\vec{J} + \frac{d\vec{D}}{dt})$$

$$= \nabla \bullet \vec{J} + \frac{d}{dt} (\nabla \bullet \vec{D}) = \nabla \bullet \vec{J} + \frac{d\rho}{dt}$$

$$\therefore \nabla \bullet \vec{J} = -\frac{d\rho}{dt}$$

The continuity eqn. is contained in Maxwell's Eqns.

34

Goddard ECE329  
Lectures 4-5

## Example: Continuity Eqn.

- For  $\mathbf{J} = J_0(x^2\mathbf{a}_x + y^2\mathbf{a}_y + z^2\mathbf{a}_z)$ , find  $d\rho/dt$  at the point  $(0.02, 0.01, 0.01)$

35

Goddard ECE329  
Lectures 4-5

From D3.6a (p 149) of old book

## Summary of Maxwell's Equations

$$\text{Faraday's Law} \quad \oint_C \vec{E} \bullet d\vec{l} = -\frac{d}{dt} \iint_S \vec{B} \bullet d\vec{S} \quad \nabla \times \vec{E} = -\frac{d\vec{B}}{dt}$$

$$\text{Ampere's Law} \quad \oint_C \vec{H} \bullet d\vec{l} = \iint_S \vec{J} \bullet d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \bullet d\vec{S} \quad \nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$$

$$\text{Gauss' Law} \quad \iint_S \vec{B} \bullet d\vec{S} = 0 \quad \nabla \bullet \vec{B} = 0$$

$$\text{Gauss' Law} \quad \iint_S \vec{D} \bullet d\vec{S} = \iiint_V \rho dV \quad \nabla \bullet \vec{D} = \rho$$

$$\text{Continuity Eq.} \quad \iint_S \vec{J} \bullet d\vec{S} = -\frac{d}{dt} \iiint_V \rho dV \quad \nabla \bullet \vec{J} = -\frac{d\rho}{dt}$$

36

Goddard ECE329  
Lectures 4-5

## Lectures 6-7 Sections 6.1-6.2

Potential Functions for Static Fields  
Poisson's and Laplace's Equation  
PN Junction


Adapted from Prof. Cunningham's Notes

1

Goddard ECE329  
Lectures 6-7

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Electric Potential



How much potential energy does a charge have in an electric field?

Answer: It depends on the work that you had to do to get it to that spot. You have to work against the E-field.

$$\Delta PE = \vec{F}_{applied} \bullet d\vec{l} = -\vec{F}_e \bullet d\vec{l}$$

$$\vec{F}_e = q\vec{E}$$

$$\Delta PE = -q\vec{E} \bullet d\vec{l}$$

Answer depends on the amount of charge  $q$   
Can we define something determined by the field only

2

Goddard ECE329  
Lectures 6-7

## Electric Potential - Definition

Work you do per unit charge is the ELECTRIC POTENTIAL DIFFERENCE between the two points

$$\Delta V = \frac{\Delta PE}{q} = -\vec{E} \bullet d\vec{l} = -E_x \Delta x \text{ if } d\vec{l} = \Delta x \hat{a}_x$$

$$\text{Units: } \frac{Nm}{C} = \frac{J}{C} = \text{VOLTS}$$

$$E_x = -\frac{\Delta V}{\Delta x}, E_y = -\frac{\Delta V}{\Delta y}, E_z = -\frac{\Delta V}{\Delta z} \quad \text{Units: } \frac{V}{m}$$

$$\vec{E} = -\vec{\nabla}V$$

3

Goddard ECE329  
Lectures 6-7

## Potential: Mount Electron




What is the steepest slope on the mountain?

4

Goddard ECE329  
Lectures 6-7

## Potential




Surfaces of equal potential  
What direction is the steepest slope at a given point?

5

Goddard ECE329  
Lectures 6-7


## Potential



Surfaces of equal potential  
Steepest downslope is:  
Opposite the gradient!  
Always perpendicular  
to surface of constant  
potential

6

Goddard ECE329  
Lectures 6-7



## Gradient Definition

$$\vec{E} = \left( \frac{\partial V}{\partial x} \hat{a}_x + \frac{\partial V}{\partial y} \hat{a}_y + \frac{\partial V}{\partial z} \hat{a}_z \right)$$

Most important definition of today:

$$\vec{E} = -\nabla V$$

$$\nabla = \left( \frac{\partial}{\partial x} \hat{a}_x + \frac{\partial}{\partial y} \hat{a}_y + \frac{\partial}{\partial z} \hat{a}_z \right)$$

Gradient Operator (Cartesian Coordinates)

8

Goddard ECE329  
Lectures 6-7

## Gradient Operator

$$\vec{E} = -\nabla V$$

$$\nabla = \left( \frac{\partial}{\partial x} \hat{a}_x + \frac{\partial}{\partial y} \hat{a}_y + \frac{\partial}{\partial z} \hat{a}_z \right)$$

$V$  is a SCALAR FIELD (potential as a function of position)

$\nabla V$  is a VECTOR FIELD

Has magnitude and direction  $-\vec{E}$

Is the DIRECTION with the FASTEST INCREASE in  $V$

Fastest direction for an electron (negative charge) to decrease its potential

9

Goddard ECE329  
Lectures 6-7

## Scalar Potentials

- For:  $\Phi_1(x, y, z) = x^2 + y^2 + z^2$   
 $\Phi_2(x, y, z) = x + 2y + 2z$

Find the following quantities at (3, 4, 12):


- the maximum rate of increase of  $\Phi_1$
- the maximum rate of increase of  $\Phi_2$
- the rate of increase of  $\Phi_1$  along the direction of the maximum rate of increase of  $\Phi_2$

10


Goddard ECE329  
Lectures 6-7

From D5.2 (p 290) of old book


## Example: Potentials for a Point Charge



## Example: Potentials for a Point Charge



### Example: Potentials for a Point Charge



$$V(r) = - \int_{\infty}^{r_i} \frac{Q}{4\pi\epsilon_0 r^2} dr$$

$$= \frac{Q}{4\pi\epsilon_0} \left( \frac{1}{r_i} - \frac{1}{\infty} \right)$$

$$= \frac{Q}{4\pi\epsilon_0 r_i}$$

Goddard ECE329  
Lectures 6-7

13

### Challenge Question: Scalar Potentials

- If the scalar potential  $V$  can be defined, which of the following is true?
- The potential difference between two points is identical, independent of path
  - The electric field is conservative
  - The electric field lines will always be perpendicular to equipotential surfaces
  - The greatest decrease in potential per unit length is along the electric field direction
  - All of the above

Goddard ECE329  
Lectures 6-7


LG's question

14

### Potential Superposition

Potentials of more than one point charge are superimposed by addition


$$V_{\text{point}} = \frac{1}{4\pi\epsilon_0} \left( \frac{Q_1}{r_1} + \frac{Q_2}{r_2} + \frac{Q_3}{r_3} + \dots \right)$$



15

Goddard ECE329  
Lectures 6-7

### Superposition Example: Potential of a Line Charge




$\rho_l = 10^{-10} \text{ C/m}$   
 $a = 1 \text{ m}$

Find Potential at point "P",  
1 m away from the line

16

Goddard ECE329  
Lectures 6-7

### Superposition Example: Potential of a Line Charge



$\rho_l = 10^{-10} \text{ C/m}$   
 $a = 1 \text{ m}$

Find Potential at point "P",  
1 m away from the line

$$V_P = \frac{1}{4\pi\epsilon_0} \int_{-a}^{a} \frac{dQ}{r}$$

$$V_P = \frac{1}{4\pi\epsilon_0} \int_{-a}^{a} \frac{\rho_l dz'}{r}$$

$$V_P = \frac{1}{4\pi\epsilon_0} \int_{-a}^{a} \frac{\rho_l dz'}{\sqrt{z'^2 + 1^2}}$$

$$V_P = \frac{\rho_l}{4\pi\epsilon_0} \ln(z' + \sqrt{z'^2 + 1}) \Big|_{-a}^{a}$$

17

Goddard ECE329  
Lectures 6-7

### Scalar Potentials

- For:  $\vec{E} = yz\hat{a}_x + (y + zx)\hat{a}_y + xy\hat{a}_z$
- Find the scalar potential if  $V(0,0,0)=0$ . (Hint: Use a direct line path. At home, try using 3 separate segments along  $x$ ,  $y$ , and  $z$  directions.)
  - Evaluate the potential difference  $V_A - V_B$  for:
    - $A=(2,1,1)$  and  $B=(1,4,0.5)$
    - $A=(2,2,2)$  and  $B=(1,1,1)$
    - $A=(5,1,0.2)$  and  $B=(1,2,3)$

Goddard ECE329  
Lectures 6-7

Adapted from D 5.4 (p299) of old book

18

## Useful facts about Potential

- Potential is always the DIFFERENCE between two points
- If one point is at infinity, then the potential is an absolute potential
- The gradient of V gives the vector -E at a particular point
- Potential between two points is identical, regardless of whether a straight or curved path is taken
  - E is a conservative field
- Electric field lines are always perpendicular to equipotential surfaces (constant voltage)
  - E-field lines are along the direction of the greatest decrease in potential

Goddard ECE329  
Lectures 6-7

19

## Gradient Function in Cylindrical and Spherical Coordinates

$\Phi$  = scalar field (like voltage)

$$\nabla \Phi = \begin{cases} \left( \frac{\partial \Phi}{\partial x} \hat{a}_x + \frac{\partial \Phi}{\partial y} \hat{a}_y + \frac{\partial \Phi}{\partial z} \hat{a}_z \right) & \text{Cartesian} \\ \left( \frac{\partial \Phi}{\partial r} \hat{a}_r + \frac{1}{r} \frac{\partial \Phi}{\partial \theta} \hat{a}_\theta + \frac{\partial \Phi}{\partial z} \hat{a}_z \right) & \text{Cylindrical} \\ \left( \frac{\partial \Phi}{\partial r} \hat{a}_r + \frac{1}{r} \frac{\partial \Phi}{\partial \theta} \hat{a}_\theta + \frac{1}{r \sin \theta} \frac{\partial \Phi}{\partial \phi} \hat{a}_\phi \right) & \text{Spherical} \end{cases}$$

20

Goddard ECE329  
Lectures 6-7

## Laplacian Operator

$$\vec{\nabla} \bullet (\nabla \Phi) = \nabla^2 \Phi$$

The "Laplacian" of a scalar field. (also called "Del Squared")

$\Phi(x, y, z)$  Scalar Field

$$\nabla \Phi = \frac{\partial \Phi}{\partial x} \hat{a}_x + \frac{\partial \Phi}{\partial y} \hat{a}_y + \frac{\partial \Phi}{\partial z} \hat{a}_z \quad \text{Vector}$$

$$\nabla^2 \Phi = \frac{\partial^2 \Phi}{\partial x^2} + \frac{\partial^2 \Phi}{\partial y^2} + \frac{\partial^2 \Phi}{\partial z^2} \quad \text{Scalar}$$

Goddard ECE329  
Lectures 6-7

21

## Poisson Equation for Potentials (static fields)

$$\vec{\nabla} \bullet (\nabla \Phi) = -\frac{\rho}{\epsilon}$$


$$\nabla^2 \Phi = -\frac{\rho}{\epsilon}$$

Known as "Poisson's Equation"  
It's just Gauss' Law in terms of Potentials for a Static Field  
If  $\rho=0$ , it is known as "Laplace's Equation"

22

Goddard ECE329  
Lectures 6-7

## Potential of pn junction (ECE 340)



- Find the scalar potential V for a step pn junction in silicon:

$$\rho = \begin{cases} -qN_A & \text{for } -d_p < x < 0 \\ qN_D & \text{for } 0 < x < d_n \\ 0 & \text{otherwise} \end{cases}$$

23

Goddard ECE329  
Lectures 6-7

From Example 5.5 (p 300) of old book

## Maxwell's Eqns - Integral form

$$\oint_C \vec{E} \bullet d\vec{l} = -\frac{d}{dt} \iint_S \vec{B} \bullet d\vec{S}$$

$$\oint_C \vec{H} \bullet d\vec{l} = \iint_S \vec{J} \bullet d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \bullet d\vec{S}$$

$$\iint_S \vec{B} \bullet d\vec{S} = 0$$


$$\iint_S \vec{D} \bullet d\vec{S} = \iiint_V \rho dV$$

They are valid for ALL closed paths and closed surfaces, EVEN WHEN THEY SPAN A BOUNDARY BETWEEN TWO MATERIALS

24

Goddard ECE329  
Lectures 6-7


## Closed Path Through a Boundary



Goddard ECE329  
 Lectures 6-7

25

## Normal Vectors



$\hat{a}_n$  Vector NORMAL to the boundary. Points INTO medium 1

$\hat{a}_s$  Vector normal to the path, TANGENT to the interface.  
 Use right hand rule for path to define direction

26

Goddard ECE329  
 Lectures 6-7

## Faraday's Law at Boundary

$$\oint_c \vec{E} \bullet d\vec{l} = -\frac{d}{dt} \iint_s \vec{B} \bullet d\vec{S} = 0$$

Medium 1 (above)  
 $\sigma_1, \epsilon_1, \mu_1$

Medium 2 (below)  
 $\sigma_2, \epsilon_2, \mu_2$


Take limit as ad and bc go to zero  
 Consider remaining  $E_1$  and  $E_2$  TANGENT TO SURFACE

$$E_1 = E_2 \text{ i.e. } E_t \text{ is continuous}$$

27

Goddard ECE329  
 Lectures 6-7

## The closed volume can enclose surface charges



Example  
 1. Free charges on the surface of a conductor

28

Goddard ECE329  
 Lectures 6-7

## Gauss' Law for D at Boundary

$$\iint_s \vec{D} \bullet d\vec{S} = \iiint_v \rho dV$$

Take limit as ae, bf, cg, and dh go to zero  
 Consider  $D_1$  and  $D_2$  NORMAL TO SURFACE  
 $D_1 - D_2 = \rho$  i.e.  $D_n$  is discontinuous because of  $\rho_s$

29

Goddard ECE329  
 Lectures 6-7

## Challenge Question: Boundary Conditions

- What is  $D_1$ ?  $\frac{\epsilon_1 = 1\epsilon_0}{\epsilon_2 = 2\epsilon_0} \quad \rho = 3 \text{ C/m}^2 \quad \vec{D}_2 = 3\hat{x} + 2\hat{y} \text{ C/m}^2$



- $3\hat{x} + 2\hat{y} \text{ C/m}^2$
- $3\hat{x} + 5\hat{y} \text{ C/m}^2$
- $3\hat{x} - 1\hat{y} \text{ C/m}^2$
- $\frac{3}{2}\hat{x} + 5\hat{y} \text{ C/m}^2$
- $\frac{3}{2}\hat{x} - 1\hat{y} \text{ C/m}^2$

Goddard ECE329  
 Lectures 6-7

LG's question

30

## Lecture 6-7 Summary

- Since  $\operatorname{div} \mathbf{D} = \rho$  and  $\mathbf{D} = \epsilon \mathbf{E}$ ,

$$\vec{E} = -\nabla \Phi$$

satisfy Gauss' Laws and is valid for static fields, if  $\epsilon$  is constant and  $\Phi$  satisfies

Poisson's equation:

$$\nabla^2 \Phi = -\frac{\rho}{\epsilon}$$

- At a boundary,  $E_{1t} = E_{2t}$  but  $D_{1n} - D_{2n} = \rho$

31

## Lectures 8-9 Section 5.1

### Conductors Dielectrics


Adapted from Prof. Cunningham's Notes

1

Goddard ECE329  
Lectures 8-9

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Atomic Model of Conductivity




- Tightly bound inner orbitals
- Loosely bound outer orbitals
- Free to escape the nucleus and move around inside the material

2

Goddard ECE329  
Lectures 8-9

## Conduction of Free Electrons



3

Goddard ECE329  
Lectures 8-9

## Conduction of free electrons

- The electron cannot travel in a straight path for very long
- It keeps running into the nuclei, getting deflected MANY times, meeting RESISTANCE
- Net motion is still in direction opposite of the applied  $\mathbf{E}$  and drift velocity is:


$$\vec{v}_d = -\mu_e \vec{E} \text{ for electrons}$$

$\mu_e = \frac{|e| \tau}{m}$  is the electron mobility,  
 $\tau \approx 10^{-14}$  sec is the average collision time

4

Goddard ECE329  
Lectures 8-9

## Holes are missing electrons




- Holes are missing electrons
  - Move in direction of  $\mathbf{E}$  field

$$\vec{v}_d = +\mu_h \vec{E} \text{ for holes}$$

5

Goddard ECE329  
Lectures 8-9

## Resistors



R tells us how much total resistance is encountered, but does not tell us anything fundamental about the resisting material

6

Goddard ECE329  
Lectures 8-9

## Resistivity

$\rho$  = Resistivity, units of ( $\Omega \cdot m$ )

- Tells us how much resistance the material provides, factoring out the dimensions of the resistor

$$R = \rho \frac{l}{A}$$

Goddard ECE329  
Lectures 8-9

7

## Conductivity

$$\sigma = \frac{1}{\text{Resistivity}} = \frac{l}{R \cdot A} = \frac{1}{\Omega \cdot m}$$

- More common to describe materials in terms of conductivity rather than resistivity
- High conductivity = low resistivity
- Special units:

$$\sigma = \frac{1}{\Omega \cdot m} = \frac{\text{Siemens}}{m} = \frac{S}{m}$$

Goddard ECE329  
Lectures 8-9

8

TABLE 2-1  
conductivities†

| Material                               | Conductivity,<br>$\Omega^{-1} m^{-1}$ | Material   | Conductivity,<br>$\Omega^{-1} m^{-1}$ |
|--|---------------------------------------|--|---------------------------------------|
| Quartz, fused                          | $-10^{-17}$                           | Silicon  | $10^3$                                |
| Ceresin wax                            | $-10^{-17}$                           | Carbon   | $-3 \times 10^4$                      |
| Polystyrene                            | $-10^{-14}$                           | Graphite   | $-10^5$                               |
| Sulfur                                 | $-10^{-13}$                           | Cast iron  | $-10^6$                               |
| Mica                                   | $-10^{-13}$                           | Mercury  | $10^6$                                |
| Paraffin                               | $-10^{-13}$                           | Nichrome   | $10^6$                                |
| Rubber, hard                           | $-10^{-13}$                           | Stainless steel  | $10^6$                                |
| Polyethylene                           | $-10^{-14}$                           | Constantan   | $2 \times 10^6$                       |
| Glass                                  | $-10^{-12}$                           | Silicon steel  | $2 \times 10^6$                       |
| Bakelite                               | $-10^{-9}$                            | German silver  | $3 \times 10^6$                       |
| Distilled water                        | $-10^{-4}$                            | Lead   | $5 \times 10^6$                       |
| Dry, sandy soil                        | $-10^{-3}$                            | Tin  | $9 \times 10^6$                       |
| Marshy soil                            | $-10^{-2}$                            | Phosphor bronze  | $10^7$                                |
| Fresh water                            | $-10^{-2}$                            | Brass  | $1 \times 10^7$                       |
| Animal fat                             | $4 \times 10^{-2}$                    | Zinc   | $1.7 \times 10^7$                     |
| Animal muscle ( $\perp$ to fiber):     | 0.08                                  | Tungsten   | $1.8 \times 10^7$                     |
| Animal muscle ( $\parallel$ to fiber): | 0.2                                   | Duralumin  | $3 \times 10^7$                       |
| Animal blood:                          | 0.35                                  | Aluminum, hard-drawn                                       | $3.5 \times 10^7$                     |
| Germanium<br>(semiconductor)           | -2                                    | Gold   | $4.1 \times 10^7$                     |
| Seawater                               | $\sim 4$                              | Copper   | $5.7 \times 10^7$                     |
| Ferrite                                | $10^2$                                | Silver   | $6.1 \times 10^7$                     |
| Tellurium                              | $\sim 5 \times 10^2$                  | Hg (at <4.1 K)   | ∞                                     |
|  |                                       | Nb (at <2.3 K)   | ∞                                     |
|  |                                       | Nb <sub>3</sub> (Al-Ge) (at <21 K)                         | ∞                                     |
|  |                                       | YBa <sub>2</sub> Cu <sub>3</sub> O <sub>7</sub> (at <80 K) | ∞                                     |

† See low frequencies. At 20°C except where noted.  
Goddard ECE329  
Lectures 8-9

9

## Conductivity

- Conductivity takes everything into account in one number
  - Number of free electrons
  - Frequency of collisions between electrons and the nuclei
  - Scattering properties of the nuclei
  - Motion for electrons and holes


$$\sigma = \mu_e N_e |e| + \mu_h N_h |e|$$

$N_e, N_h$  = # of free electrons or holes per  $\text{cm}^3$

10

## Ohm's Law

$$|E| = \frac{V}{l} \quad (\frac{V}{m})$$



$$|J| = \frac{I}{A} \quad (\frac{A}{m^2})$$

$$R = \frac{l}{\sigma A} \quad (\Omega)$$

$$V = IR$$

$$E \cdot l = (J \cdot A)(\frac{l}{\sigma A}) = \frac{1}{\sigma} J \cdot l$$

$$J = \sigma E$$

11

Goddard ECE329  
Lectures 8-9

## Maxwell's Equations in a Conductor

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t} \quad \text{In free space}$$

$$\vec{\nabla} \times \vec{H} = \sigma \vec{E} + \frac{\partial \vec{D}}{\partial t} \quad \text{In a conducting material}$$

Conduction current:  
Moving charge


Displacement Current:  
Time varying E-field

Goddard ECE329  
Lectures 8-9

12

## Perfect Conductor (PC) in an Applied Electric Field

Air




What Happens?

13

Goddard ECE329  
Lectures 8-9

## Perfect Conductor (PC) in an Applied Electric Field

Air



E<sub>Applied</sub>

What Happens?


- Free e<sup>-</sup> move in direction opposite of applied E
- When e<sup>-</sup> moves away from its nucleus, it leaves a + charge behind
- The material as a whole is still NEUTRALLY CHARGED but the charge has now been redistributed

14

Goddard ECE329  
Lectures 8-9

## E=0 inside perfect conductor

Air



What Happens Next?


- The separated + and - charges create their own SECONDARY INTERNAL E field that EXACTLY CANCELS the applied E field
- The TOTAL E field inside the perfect conductor is ALWAYS ZERO
- If it weren't zero, free charge would continue drifting till it is!

15

Goddard ECE329  
Lectures 8-9

## Infinite plane conducting slab

- An infinite plane conducting slab lies between two infinite plane sheets of uniform charge density  $\rho_A$  and  $\rho_B$ . Find the surface charge densities on the two slab surfaces.



16

Goddard ECE329  
Lectures 8-9

From D4.2 (p 217) of old book

## If E=0 inside a PC, how about H?

$$\vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t} \Rightarrow 0 = -\frac{\partial \vec{B}}{\partial t}$$

B and H must be STATIC


Technically, a non-zero static H-field can exist inside a PC, but how did it get there? It must have existed there for all time. But, then what created it in the first place. This is an ill-posed problem so in 329, we will assume H=0 inside a PC.

17

Goddard ECE329  
Lectures 8-9

## Challenge Question: Point charge above a sheet

- A positive charge is located above a perfectly conducting infinite ground plane at  $z=0$



- E=0 above the plane
- E=0 below the plane
- A uniform charge density is induced on the plane
- The total induced charge on the plane is +Q
- The electric field lines have a radial component at the plane

18

Goddard ECE329  
Lectures 8-9

LG's question

## Lecture 8 Summary

- Ohm's Law:
- Conductivity:  $\sigma = \frac{1}{\text{Resistivity}} = \frac{l}{R \cdot A}$
- Inside a perfect conductor,  $\mathbf{E} =$
- Next class
  - Dielectrics

Goddard ECE329  
Lectures 8-9

19


## ECE 329 Lecture 9

### Dielectrics

Adapted from Prof. Cunningham's Notes

20

## Atomic Model of Dielectric Polarization




- Tightly bound inner orbitals
- Not many loosely bound outer orbital electrons

Goddard ECE329  
Lectures 8-9


21

## Polarization of an atom



Goddard ECE329  
Lectures 8-9


## Polarization of an atom



Goddard ECE329  
Lectures 8-9

## Polarization or Electric Dipole Moment per Unit Volume

"mini" dipole moment  
for one atom





$\mathbf{d}$  is the distance VECTOR going from “-” to “+” side

$\mathbf{p} = Q\mathbf{d}$  is the electric dipole moment

Goddard ECE329  
Lectures 8-9

24



### Dielectric Susceptibility $\chi_e$

- Measures how easy it is to shift electrons from their centered orbit around the nuclei of a material to form internal dipoles

$$\vec{P} = \epsilon_0 \chi_e \vec{E}_{tot}$$

27

Goddard ECE329  
Lectures 8-9

### Apply $\mathbf{E}$ to Dielectric Material

Cancellation of internal charges

28

Goddard ECE329  
Lectures 8-9

"Polarization Surface Charges" Remain

### Apply $\mathbf{E}$ to Dielectric Material

Cancellation of internal charges

29

Goddard ECE329  
Lectures 8-9

Secondary Electric Field Produced  
\* Does not cancel applied field inside dielectric

### $\mathbf{E}_{tot}$ is reduced but not zero

Unlike conductors where  $\mathbf{E}=0$ , in the dielectric slab, the total field is **reduced (but NOT eliminated)** by the secondary field produced by the surface polarization charge

$$\vec{E}_{tot} = \vec{E}_a + \vec{E}_s$$

And the polarization vector,  $\mathbf{P}$ , is the polarization of atoms in the dielectric due to the TOTAL field (after it has been reduced by  $\mathbf{E}_s$ )


$$\vec{P} = \epsilon_0 \chi_e \vec{E}_{tot}$$

30

Goddard ECE329  
Lectures 8-9

## Example


- Apply external electric field to a slab of dielectric material
- Apply field by placing the slab between two equal and opposite charge densities



Goddard ECE329  
Lectures 8-9

31

## Example



32

## Example

$$\vec{E}_{Secondary} = -\frac{\rho_p}{\epsilon_0} \hat{a}_z$$

$$Dielectric\ slab,\ \chi_e$$

$$+\rho_p \quad -\rho_p$$

$$\vec{E}_{Applied} = \frac{\rho_{s0}}{\epsilon_0} \hat{a}_z$$

$$\vec{E}_{Total} = \vec{E}_{Applied} + \vec{E}_{Secondary}$$

$$\vec{P} = \epsilon_0 \chi_e \vec{E}_{total} = \chi_e (\rho_{s0} - \rho_p) \hat{a}_z$$

But how much charge  $\rho_p$  is generated by  $\rho_{s0}$ ??

Goddard ECE329  
Lectures 8-9

33

## Example

$$\Delta S$$

$$d$$

$$+\rho_p \quad -\rho_p$$

$$\vec{P} = P_0 \hat{a}_z$$

$$\vec{PV} = P_0 (d\Delta S) \hat{a}_z$$

$$Q\vec{d} = (\rho_p \Delta S) d \hat{a}_z$$

where  $P_0$  is the dipole moment per unit volume

the total dipole moment of the column

also the total dipole moment of the column

$$\therefore P_0 = \rho_p \quad \text{dipole moment per unit volume} = \text{surface charge density}$$

34

## Example

$$E_{Secondary} = -\frac{P_0}{\epsilon_0} \hat{a}_z$$

$$+\rho_p \quad -\rho_p$$

$$Dielectric\ slab,\ \chi_e$$

$$\vec{E}_{Applied} = \frac{\rho_{s0}}{\epsilon_0} \hat{a}_z$$

$$\vec{P} = \epsilon_0 \chi_e \vec{E}_{total} = \chi_e (\rho_{s0} - \rho_p) \hat{a}_z$$

$$P_0 \hat{a}_z = \chi_e (\rho_{s0} - \rho_p) \hat{a}_z = \chi_e (\rho_{s0} - P_0) \hat{a}_z$$

$$P_0 = \chi_e \rho_{s0} - \chi_e P_0 \quad \therefore \rho_p = P_0 = \frac{\chi_e \rho_{s0}}{1 + \chi_e}$$

Goddard ECE329  
Lectures 8-9

35

## Example

So finally, the “final answer” is:

$$\vec{E}_{Total} = \frac{P_0}{\epsilon_0 \chi_e} = \frac{\rho_{s0}/\epsilon_0}{1 + \chi_e}$$


The total electric field strength inside the dielectric is reduced from its “free space” value by  $(1 + \chi_e)$

Free space:  $\chi_e = 0$       Perfect Conductor:  $\chi_e \rightarrow \infty$

36

Goddard ECE329  
Lectures 8-9

## Dipole Atoms in Alternating E Field



Moving charges means a current  
Definition of the "Polarization Current"  $I_p = \frac{dQ}{dt}$

Goddard ECE329  
Lectures 8-9

37

## Recall from the Example

$\bar{P} = P_0 \hat{a}_z$  where  $P_0$  is the dipole moment per unit volume

$\bar{P}V = P_0(d\Delta S)\hat{a}_z$  the total dipole moment of the column

$Q\bar{d} = (\rho_p \Delta S)d\hat{a}_z$  also the total dipole moment of the column

$$P_0 \Delta S = Q$$

$$\therefore J_p = \frac{I_p}{\Delta S} = \frac{dQ/dt}{\Delta S} = \frac{dP_0}{dt}$$

38

## Polarization Current

- Application of an alternating **E** field results in a polarization current due to motion of charge between the two surfaces of the dielectric material

$$\vec{J}_p = \frac{\partial \vec{P}}{\partial t}$$

39

Goddard ECE329  
Lectures 8-9

## Ampere's Law in a Dielectric

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$$

In a dielectric medium, we need to include  $J_p$  with the total current

$$\vec{\nabla} \times \vec{H} = \vec{J} + \vec{J}_p + \frac{\partial(\epsilon_0 \vec{E}_{total})}{\partial t}$$

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{P}}{\partial t} + \frac{\partial(\epsilon_0 \vec{E}_{total})}{\partial t}$$

40

Goddard ECE329  
Lectures 8-9

## Ampere's Law in a Dielectric

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{P}}{\partial t} + \frac{\partial(\epsilon_0 \vec{E}_{total})}{\partial t}$$

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial}{\partial t} (\vec{P} + \epsilon_0 \vec{E}_{total})$$

So Ampere's law is the same and we modify the displacement vector's definition

$$\vec{D} = \vec{P} + \epsilon_0 \vec{E}_{total}$$

41

Goddard ECE329  
Lectures 8-9

## Definition of Dielectric Constant

$$\vec{D} = \vec{P} + \epsilon_0 \vec{E}_{total}$$

$$\vec{D} = \epsilon_0 \chi_e \vec{E}_{total} + \epsilon_0 \vec{E}_{total}$$

$$\vec{D} = \epsilon_0 (1 + \chi_e) \vec{E}_{total}$$

$$\vec{D} = \epsilon_0 \epsilon_r \vec{E}_{total}$$

42

Goddard ECE329  
Lectures 8-9

## Definition of Dielectric Constant

$$\vec{D} = \epsilon_0 \epsilon_r \vec{E}_{total}$$

Relative Permittivity = "Dielectric Constant"

$$\epsilon_r = (1 + \chi_e)$$

Dielectric Permittivity of the Material

$$\epsilon = \epsilon_0 \epsilon_r$$

$$\vec{D} = \epsilon \vec{E}_{total}$$

Units for  $\epsilon_r$ : None

43

Goddard ECE329  
Lectures 8-9

## Ampere's Law in a Dielectric

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$$

with

$$\vec{D} = \epsilon \vec{E}_{total}$$


No need to worry about polarization current - it is all incorporated into the "new" definition for  $\mathbf{D}$

Generally we can use Maxwell's equations to solve for  $\mathbf{D}$  and then calculate  $\mathbf{E}_{total}$

44

Goddard ECE329  
Lectures 8-9

## Recall Example



Goddard ECE329  
Lectures 8-9

45

## Infinite plane dielectric slab

- An infinite plane dielectric slab lies between two infinite plane sheets of uniform charge density of  $\rho = \pm 1 \mu C/m^2$ . Find  $\mathbf{D}$ ,  $\mathbf{E}$ , and  $\mathbf{P}$  inside the slab.

Hint: 
$$\begin{aligned} \mathbf{D} &= (\rho/2) \hat{a}_z & \rho \\ \mathbf{D} &= -(\rho/2) \hat{a}_z \end{aligned}$$

Goddard ECE329  
Lectures 8-9

From D4.3 (p 226) of old book

46

## Challenge Question: Spherical shell dielectric

- If we have: 
$$\begin{cases} r < a & \text{perfect conductor} \\ a < r < b & \text{perfect dielectric } \epsilon = 3\epsilon_0 \\ r > b & \text{perfect conductor} \end{cases}$$

with equally and oppositely charged PCs and  $\mathbf{D}$  points radially inward, which is true:

- $V(b) > V(a)$
- $V(b) = V(a)$
- $V(b) < V(a)$

47

Goddard ECE329  
Lectures 8-9

LG's question

## Lecture 9 Summary

- Electric dipole moment  $\mathbf{p} = q\mathbf{d}$
- Polarization or electric dipole moment per unit volume
  - $\mathbf{P} = N\mathbf{p} = \epsilon_0 \chi_e \mathbf{E}_{total} = \epsilon_0 \chi_e (\mathbf{E}_a + \mathbf{E}_s)$
  - Simple linear isotropic dielectric
    - Reduces  $\mathbf{E}$ -field strength by  $(1 + \chi_e)$
    - $\mathbf{D}$  has same value as free space
    - Polarization current  $\mathbf{J}_p = d\mathbf{P}/dt$
    - New definition  $\mathbf{D} = \mathbf{P} + \epsilon_0 \mathbf{E}_{total} = \epsilon \mathbf{E}_{total}$
- Next class
  - Capacitance and Conductance

Goddard ECE329  
Lectures 8-9

48

# ECE 329

## Lectures 10-11

### Sections 6.3, 5.1

Capacitance and Conductance  
Conductivity and Susceptibility


Adapted from Prof. Cunningham's Notes

1

Goddard ECE329  
Lectures 10-11

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Parallel-plate Capacitor




$$\text{Capacitance is: } C = Q/V_0$$

2

Goddard ECE329  
Lectures 10-11

## Steps to Find Capacitance




- Laplace Equation  $\vec{\nabla}^2 V = 0$
- Find  $V$  using boundary conditions
- Find  $\mathbf{E}$  using  $\vec{E} = -\vec{\nabla}V$
- Find  $\mathbf{D}$  using  $\vec{D} = \epsilon \vec{E}$
- Get surface charge density on one conductor using BC  $\rho_s = \vec{a}_n \bullet (\vec{D}_{n1} - \vec{D}_{n2})$   $\rho = \epsilon V_0 / d$
- Charge  $Q = (\text{Area})(\rho_s)$
- Capacitance  $C = Q/V_0$

$$V(x) = V_0 \frac{x}{d}$$

$$C = \frac{\epsilon A}{d}$$

Goddard ECE329  
Lectures 10-11

## Non-uniform permittivity




$$\epsilon(x) = \frac{\epsilon_0}{1 + x/d}$$

4

Goddard ECE329  
Lectures 10-11

From P5.20 (p352) of old book


## Coaxial Cable



5

Goddard ECE329  
Lectures 10-11

## Coaxial Cable



$$\nabla^2 V = \frac{1}{r} \frac{\partial}{\partial r} (r \frac{\partial V}{\partial r}) = 0$$

$$\rho = \begin{cases} \epsilon V_0 / (a \ln(b/a)), & r = a \\ -\epsilon V_0 / (b \ln(b/a)), & r = b \end{cases}$$

$$C = \frac{2\pi\epsilon L}{\ln(b/a)}$$

Goddard ECE329  
Lectures 10-11

## Challenge Question: Coaxial cable capacitance

- Consider a coax with ( $\epsilon_{\text{old}}=3\epsilon_0$ ) for  $a < r < b$ . If we remove the dielectric and replace it with free space ( $\epsilon_{\text{new}}=\epsilon_0$ ) but **keep the same amount of charge** on each PC, which is **false**:
  - the voltage across the capacitor is reduced by 3x
  - the capacitance is reduced by 3x
  - the E-field for  $a < r < b$  is increased by 3x
  - the D-field for  $a < r < b$  is unchanged

Goddard ECE329  
Lectures 10-11

LG's question

7

## Challenge Question: Coaxial cable capacitance


- Consider a coax with ( $\epsilon_{\text{old}}=3\epsilon_0$ ) for  $a < r < b$ . If we remove the dielectric and replace it with free space ( $\epsilon_{\text{new}}=\epsilon_0$ ) but **keep the same voltage** across the coax, which is **false**:
  - the charge across the capacitor is reduced by 3x
  - the capacitance is reduced by 3x
  - the E-field for  $a < r < b$  is reduced by 3x
  - the D-field for  $a < r < b$  is reduced by 3x

Goddard ECE329  
Lectures 10-11

LG's question

8

## Conductance



Now a current can flow  $x=d$  to  $x=0$

$$\vec{J}_c = \sigma \vec{E} = \sigma \left( \frac{V_0}{d} \right) (-\vec{a}_x)$$

Current density (A/m<sup>2</sup>)

9

Goddard ECE329  
Lectures 10-11

## Conductance

$$G = \frac{|I_c|}{V_0}$$

Conductance  
Units: Siemens


For the parallel plate capacitor

$$G = \frac{\sigma A}{d}$$

10

Goddard ECE329  
Lectures 10-11


## Conductance/Length for Coaxial Cable



$$\vec{E} = \frac{V_0}{\ln(b/a)} \left( \frac{1}{r} \right) \vec{a}_r$$

so

$$\vec{J}_c = \sigma \vec{E} = \frac{\sigma V_0}{\ln(b/a)} \left( \frac{1}{r} \right) \vec{a}_r \quad [A/m^2]$$



What is radial current ( $I_c$ ) for a fixed length of the cable?

Goddard ECE329  
Lectures 10-11

11

## Conductance/Length of Coaxial Cable

$$I_c = \int \vec{J} \bullet d\vec{S} \quad [A]$$

$$I_c = \int_{\phi=0}^{2\pi} \int_{z=0}^L J_c (r d\phi dz)$$

$$I_c = \frac{2\pi\sigma V_0 L}{\ln(b/a)}$$

$$G = \frac{I_c}{V_0} = \frac{2\pi\sigma L}{\ln(b/a)} \quad [\text{Siemens}]$$

$$G = \frac{G}{L} = \frac{2\pi\sigma}{\ln(b/a)} \quad [S/m]$$

12

Goddard ECE329  
Lectures 10-11

## Steps for Finding Conductance

- Find Electric Field
- Find Conduction Current Density (A/m<sup>2</sup>)  $\vec{J}_c = \sigma \vec{E}$
- Conduction Current (A)  $I_c = \int \vec{J} \bullet d\vec{s}$
- Conductance  $G = \frac{I_c}{V_0}$
- Conductance/Length

13

Goddard ECE329  
Lectures 10-11

## (Optional) The Laplace Transform

- Can be used for Transmission Line analysis
  - Method to solve Initial Value Differential Equations

$$\mathcal{L}\{f(t)\} = F(s) = \int_0^{\infty} e^{-st} f(t) dt$$

- Most useful property - it converts differential equations in time to algebraic ones in s-space:

$$\mathcal{L}\{f'(t)\} = sF(s) - f(0)$$

$$\mathcal{L}\{f^{(n)}(t)\} = s^n F(s) - s^{n-1} f(0) - s^{n-2} f'(0) - \dots - s f^{(n-2)}(0) - f^{(n-1)}(0)$$

14

Goddard ECE329  
Lectures 10-11

## (Optional) The Laplace Transform


- Key Transformations are the following:

| $f(t) = \mathcal{L}^{-1}\{F(s)\}$ | $F(s) = \mathcal{L}\{f(t)\}$ |
|-----------------------------------|------------------------------|
| 1                                 | $1/s$                        |
| $e^{at}$                          | $1/(s-a)$                    |
| $t^n$                             | $n!/s^{n+1}$                 |
| $u(t-c)$                          | $e^{-cs}/s$                  |
| $u(t-c)f(t-c)$                    | $e^{-cs}F(s)$                |
| $e^{ct}f(t)$                      | $F(s-c)$                     |
| $f(ct)$                           | $1/c F(s/c)$                 |
| $\delta(t-c)$                     | $e^{-cs}$                    |
| $\int_0^t f(t-\tau)g(\tau)d\tau$  | $F(s)G(s)$                   |

15

Goddard ECE329  
Lectures 10-11

## (Optional) Application of the Laplace Transform



$$IR + L \frac{dI}{dt} = 0$$

$$\mathcal{L}\left\{IR + L \frac{dI}{dt}\right\} = 0$$

$$F(s)R + (sF(s) - I_0) \cdot L = 0$$

$$F(s) = \frac{I_0 L}{R + sL} = \frac{I_0}{s + R/L}$$

$$\mathcal{L}\{e^{at}\} = \frac{1}{s-a} \Rightarrow I(t) = I_0 e^{-\frac{R}{L}t}$$

16

Goddard ECE329  
Lectures 10-11

## Lecture 10 Summary

- Capacitance  $C = Q/V_0$
- Conductance  $G = |I_c|/V_0$
- Next Up
  - Conductivity and Susceptibility

17

Goddard ECE329  
Lectures 10-11

## Lecture 11

Bound charge  
Modeling  $\chi$  and  $\epsilon$


18

Goddard ECE329  
Lectures 10-11

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## The Lorentz-Drude model

- With applied  $\mathbf{E}$ , the mean position of free charge  $q > 0$  drifts in direction  $E$  with mean velocity  $\mathbf{v}$ : balance of acceleration due to  $E$  and friction from collisions with lattice at random intervals with mean time  $\tau$



Goddard ECE329  
Lectures 10-11

19

## The Lorentz-Drude model: DC conductivity

- If  $\mathbf{E}=0$ , charge eventually slows to  $\mathbf{v}=0$ :  $\vec{v}(t) = v_0 e^{-t/\tau}$
- But, with a constant  $\mathbf{E}$ , the steady state solution is:

$$\vec{v}(t=\infty) = \frac{q\tau}{m} \vec{E} = \mu \vec{E} \quad \mu = \frac{q\tau}{m}$$

charge mobility. For  $N$  charges per unit volume, the total current becomes:

$$\bar{I} = \frac{dQ}{dt} = \frac{qN\Delta V}{\Delta t} = \frac{qNA\vec{v}\Delta t}{\Delta t} = qNA\vec{v}$$

$$\bar{J} = \frac{\bar{I}}{A} = qN\vec{v} = \frac{Nq^2\tau}{m} \vec{E}$$

Goddard ECE329  
Lectures 10-11

20

## Ohm's Law!

$$\bar{J} = \frac{\bar{I}}{A} = qN\vec{v} = \frac{Nq^2\tau}{m} \vec{E}$$

$$\bar{J} = \sigma \vec{E} \text{ where } \sigma = \frac{Nq^2\tau}{m} = \frac{Nq^2}{m\varpi}$$

where  $\varpi \equiv \frac{1}{\tau}$  is the collision frequency

Goddard ECE329  
Lectures 10-11

21

## Review of PHASORS



Spock, set your TI-89 to  
"STUN", not "KILL"!!!



Sorry Captain, I promise not to  
harm another ECE329 student.  
Next time, I will set the Phasor  
to "AWAKEN" instead!

22


## Phasor Review - Complex #'s

$$a + jb = \bar{A} = Ae^{j\theta}$$

$$Ae^{j\theta} = A \cos \theta + jA \sin \theta$$

$$A = \sqrt{a^2 + b^2}$$

$$\theta = \tan^{-1} \frac{b}{a}$$



23

Goddard ECE329  
Lectures 10-11

## Phasor Review - Complex #'s

$$Ae^{jx} = A \cos(x) + jA \sin(x)$$

$$A \cos(x) = \operatorname{Re}[Ae^{jx}]$$

$$A \sin(x) = \operatorname{Im}[Ae^{jx}] = \operatorname{Re}[-jAe^{jx}] = \operatorname{Re}[Ae^{j(x-\pi/2)}]$$

Write  $5 \cos(\omega t) + 10 \sin(\omega t - 30^\circ)$  as a phasor

Goddard ECE329  
Lectures 10-11

24

## Phasor Review with vectors

$$e^{j\theta} = \cos \theta + j \sin \theta$$


$$\cos(\theta) = \operatorname{Re}[e^{j\theta}]$$

$$\sin(\theta) = \operatorname{Re}[-je^{j\theta}] = \operatorname{Re}[e^{j(\theta-\pi/2)}]$$

$$\operatorname{Re}[z] = (z + z^*)/2$$

$$\begin{aligned} E_x(z, t) &= E_x(z) \cos(\omega t \mp \beta z + \theta) \\ &= \operatorname{Re}[E_x(z) e^{\mp j\beta z} e^{j\theta} e^{j\omega t}] \\ &= \operatorname{Re}[\bar{E}_x(z) e^{j\omega t}] \end{aligned}$$

Goddard ECE329  
Lectures 10-11



25

## The Lorentz-Drude model: AC conductivity

- If  $\mathbf{E}$  is time varying, we use phasors to analyze the response:

$$\vec{E}(t) = \operatorname{Re}\{\tilde{E}e^{j\omega t}\}$$

$$\vec{v}(t) = \operatorname{Re}\{\tilde{v}e^{j\omega t}\}$$

$$\vec{J}(t) = \operatorname{Re}\{\tilde{J}e^{j\omega t}\}$$

- Note that:  $\tilde{E}$  and  $\tilde{J}$  are vectors and complex valued

$$(e.g. \tilde{E} = 3.2e^{j\pi/4}\hat{x} - 1.3e^{j\pi/6}\hat{y})$$

26

Goddard ECE329  
Lectures 10-11

## The Lorentz-Drude model: AC conductivity

- We can now transform the force equation from a differential one to an algebraic one ( $d/dt = j\omega$ ):

$$m \frac{d\vec{v}}{dt} = q\vec{E} - m \frac{\vec{v}}{\tau} \Rightarrow m j \omega \tilde{v} = q \tilde{E} - m \varpi \tilde{v}$$

and thus, we get:

$$\tilde{v} = \frac{q \tilde{E}}{m j \omega + m \varpi} \Rightarrow \tilde{J} = q N \tilde{v} = \frac{N q^2}{m(j\omega + \varpi)} \vec{E}$$

$$\sigma = \frac{N q^2}{m(j\omega + \varpi)}$$

27

Goddard ECE329  
Lectures 10-11

## Challenge Question: AC conductivity

- We found:  $\sigma = \frac{N q^2}{m(j\omega + \varpi)}$

- At all finite frequencies, energy is being lost to Joule heating
- At low frequency (DC),  $J$  and  $E$  are in phase
- At very high frequency ( $\omega \gg \varpi$ ),  $J$  and  $E$  are  $90^\circ$  out of phase

Which of the following is true:

- I only, (b) II only, (c) III only,
- (d) I, II, and III, (e) None are true

28

Goddard ECE329  
Lectures 10-11

LG's question

## (Preview) Time Averaged Poynting Vector

$$\vec{E} = \operatorname{Re}[\bar{E}e^{j\omega t}] = \frac{1}{2}(\bar{E}e^{j\omega t} + \bar{E}^*e^{-j\omega t}) \quad \vec{H} = \operatorname{Re}[\bar{H}e^{j\omega t}]$$

$$\langle \vec{P} \rangle = \langle \vec{E} \times \vec{H} \rangle = \left\langle \frac{\bar{E}e^{j\omega t} + \bar{E}^*e^{-j\omega t}}{2} \times \frac{\bar{H}e^{j\omega t} + \bar{H}^*e^{-j\omega t}}{2} \right\rangle$$

$$= \frac{1}{4} \left\langle \bar{E} \times \bar{H} e^{2j\omega t} + \bar{E} \times \bar{H}^* + \bar{E}^* \times \bar{H} + \bar{E}^* \times \bar{H}^* e^{-2j\omega t} \right\rangle$$


$$\langle \vec{P} \rangle = \frac{1}{2} \operatorname{Re}[\bar{E} \times \bar{H}^*]$$

29

Goddard ECE329  
Lectures 10-11

## Susceptibility

- A perfect dielectric is defined by  $\sigma=0$  so since  $\sigma = \frac{N q^2}{m(j\omega + \varpi)}$ , there can't be any free charge inside ( $N=0$ )
- The dielectric can have bound charge and we know it can be polarized:



if the nucleus is located at the origin

- The electron's motion is described by:

$$\vec{F} = m\ddot{\vec{r}} = m \frac{d^2\vec{r}}{dt^2} = -q\vec{E} - 2m\alpha \frac{d\vec{r}}{dt} - m\omega_0^2 \vec{r}$$

where  $-m\omega_0^2 \vec{r}$  describes the spring like restoring force to the nucleus and  $-2m\alpha \vec{v}$  is a friction like damping force


30

Goddard ECE329  
Lectures 10-11

## DC Susceptibility

- For DC,  $d/dt = 0$  so we get

$$\vec{r} = -\frac{q\vec{E}}{m\omega_0^2}$$



and so:  $p = -q\vec{r} = \frac{q^2}{m\omega_0^2} \vec{E}$

and thus:  $P = N_d p = \frac{N_d q^2}{m\omega_0^2} \vec{E} = \epsilon_0 \chi_e \vec{E}$

where:  $\chi_e = \frac{N_d q^2}{m\omega_0^2 \epsilon_0}$

Note:  $N_d$  (# of dipoles per vol)  $\neq N$  (# of free charge per vol)

Can use phasors to derive AC susceptibility:  $\chi_e(\omega)$

31

Goddard ECE329  
Lectures 10-11

## Lecture 11 Summary

- AC Conductivity:

$$\sigma = \frac{Nq^2}{m(j\omega + \sigma)}$$

- DC Susceptibility:

$$\chi_e = \frac{N_d q^2}{m\omega_0^2 \epsilon_0}$$

### Next Up

- Magnetic Force, Ampere's law, current sheets, Faraday's law (1.6, 2.4, 2.3)

32

Goddard ECE329  
Lectures 10-11

## Lectures 12-14

### Sections 1.6, 2.4, 2.1, 2.3

- Magnetic Fields
- Biot-Savart Law
- Ampere's Law
- Displacement Current
- Faraday's Law

Adapted from Prof. Cunningham's Notes


1

Goddard ECE329  
Lectures 12-14

© 2007, Lyndon Goddard - Copying, publishing or distributing without express written permission is prohibited

## Magnetism and Electricity

Andre Marie Ampere - 1820



Parallel Currents in Same Direction ATTRACT

Parallel Currents in Opposite Direction REPEL

2

Goddard ECE329  
Lectures 12-14



## Ampere's observations

- The magnitude of  $F$  is
  - proportional to the product of the currents AND to the product of their lengths
  - inversely proportional to the square of the distance
  - depends on the medium
- The direction of  $F$  on current 1 is
  - perpendicular to  $dI_1$
  - perpendicular to  $dI_2 \times a_{21}$
- The forces  $dF_1$  and  $dF_2$  are not always equal and opposite

3

Goddard ECE329  
Lectures 12-14

## Magnetic Field of Bar Magnet




UNLIKE poles ATTRACT  
LIKE poles REPEL  
(same as electric charges)

4

Goddard ECE329  
Lectures 12-14

## Magnetism and Electricity

Hans Oersted - 1821




Magnets line up  
in the presence of  
a nearby current

5

Goddard ECE329  
Lectures 12-14

## Magnetic Flux Lines



Magnetic flux lines form a VECTOR FIELD

Density of lines indicates MAGNITUDE


Direction = the way our compass would point

Unlike electric field lines which begin on positive charges and end on negative charges, magnetic flux lines NEVER begin or end

6

Goddard ECE329  
Lectures 12-14

## Magnetic Flux Lines



Goddard ECE329  
Lectures 12-14

## Current = Moving Charge

What is CURRENT? CHARGES IN MOTION!!

$$I d\vec{l}$$

$$\frac{\text{coul}}{\text{sec}} \cdot m = \text{coul} \cdot \frac{m}{\text{sec}}$$


So the current in a wire,  $I$ , flowing across a magnetic field will feel a force...

$$F_M = (I d\vec{l}) \times \vec{B} = q \vec{v} \times \vec{B}$$

8

Goddard ECE329  
Lectures 12-14

## Ampere's Force Law




Goddard ECE329  
Lectures 12-14

Force on current 1 due to current 2 depends on the Magnetic field at 1 due to current 2.

9

## Biot-Savart Law for finding $\mathbf{B}$



Magnetic field at point 1 due to current 2

10

Goddard ECE329  
Lectures 12-14

## Force between two wires

Combining these results,

$$dF = (I_1 d\vec{l}_1) \times \left( \frac{\mu_0}{4\pi} \cdot \frac{I_2 d\vec{l}_2 \times \hat{a}_R}{R^2} \right)$$

Magnetic flux density caused by #2 at #1


$$dF_{at\ 1} = (I_1 d\vec{l}_1) \times \vec{B}$$

To find the total force on wire 1, we add up (integrate) the contributions from segments  $d\vec{l}_2$  for every  $d\vec{l}_1$  (double integral)

11

Goddard ECE329  
Lectures 12-14

## Example: Find $\mathbf{B}$ for an Infinite Line of Current



Wire carrying current in +z direction =  $I$  (A)  
Find  $\mathbf{B}$  for any arbitrary point  $P(r, \phi, z)$  in cylindrical coords

12

Goddard ECE329  
Lectures 12-14

## Patented 5-Step Program for Problem Solving

### 1. MAKE A **LARGE CLEAR** DRAWING

- a. Also draw cross-sections if the problem is in 3D
- b. Pick a coordinate system that is appropriate for the symmetry of the problem

### 2. Divide current distributions into tiny pieces

### 3. Find $d\mathbf{B}$ of one tiny piece

### 4. Use SYMMETRY to eliminate any components that cancel (i.e. add to ZERO)

### 5. INTEGRATE to add contribution of ALL the tiny pieces

13

Goddard ECE329  
Lectures 12-14

- Step 1 - draw a picture  
Step 2 - divide the line into segments  $d\vec{l}$   
Step 3 - find  $d\mathbf{B}$  for one small segment

$$d\vec{l} = Idz \hat{a}_z$$

$$d\vec{B} = \frac{\mu_0}{4\pi} \frac{Idl \times \hat{a}_R}{R^2}$$

$$d\vec{B} = \frac{\mu_0}{4\pi} \frac{Idz \sin(90 + \alpha)}{R^2} \hat{a}_\phi$$

$$d\vec{B} = \frac{\mu_0}{4\pi} \frac{Idz}{R^3} \frac{r}{R} \hat{a}_\phi$$

$$\vec{B}(r, \phi, 0)$$

14

Goddard ECE329  
Lectures 12-14

- Step 4: Use symmetry to eliminate components  
Step 5: Integrate over the whole object

TANGENTIAL View

$$z = r \tan(\alpha)$$

$$R = r/\cos(\alpha)$$

$$dz = r \sec^2(\alpha) d\alpha$$

$$d\vec{B} = \frac{\mu_0}{4\pi} \frac{I}{(r/\cos(\alpha))^3} d\alpha \hat{a}_\phi$$

$$\vec{B} = \frac{\mu_0 I}{4\pi r} \hat{a}_\phi \int_{-\pi/2}^{\pi/2} \cos(\alpha) d\alpha = \frac{\mu_0 I}{2\pi r} \hat{a}_\phi$$

TOP View

15

Goddard ECE329  
Lectures 12-14

## Magnetic flux density ( $\mathbf{B}$ ) around a line of current

$$\vec{B} = \frac{\mu_0 I}{2\pi r} \vec{a}_\phi$$

Right hand rule  
Curl fingers around current

Practice sketching field lines:



16

Goddard ECE329  
Lectures 12-14

## "Static" Ampere's Law

Let's integrate  $\mathbf{B}$  over any circular path centered on the wire:

$$\oint_C \vec{B} \bullet d\vec{l} = \int_{\phi=0}^{2\pi} \left( \frac{\mu_0 I}{2\pi r} \hat{a}_\phi \right) \bullet (r d\phi \hat{a}_\phi)$$

$$= \int_{\phi=0}^{2\pi} \left( \frac{\mu_0 I}{2\pi} \right)$$

$$= \mu_0 I$$

So...  $\oint_C \frac{\vec{B}}{\mu_0} \bullet d\vec{l} = I$  for any radius circle

Goddard ECE329  
Lectures 12-14

## New Definition: Magnetic Field Intensity Vector

$$\oint_C \vec{H} \bullet d\vec{l} = I_{\text{enclosed}}$$

$$\vec{H} = \frac{\vec{B}}{\mu_0}$$

Units: (A/m)

18

Goddard ECE329  
Lectures 12-14

## Current Distributions

Line Current



$$\vec{I} = \text{Amps}(A)$$


Surface Current



$$\vec{J}_s = \frac{A}{m}$$

length

Volume Current



$$\vec{J}_v = \frac{A}{m^2}$$

length


height

Goddard ECE329  
Lectures 12-14

19

## Challenge Question

- A coaxial cable has a solid center wire and an outer cylindrical shell wire. A uniform current density  $J$  flows in the direction  $-\mathbf{a}_x$  on the inner wire and the total current returns on the outer shell. In which region(s) will the B-field be constant?




- $r < a$
- $a < r < b$
- $r > b$
- both (b) and (c)

Goddard ECE329  
Lectures 12-14

20

## Static Ampere's Law

Open Surface, where the Path forms a "Mouth"




$$\oint \vec{H} \cdot d\vec{l} = I_{\text{enclosed}} = \iint_S \vec{J} \cdot d\vec{S}$$

In general, all the current entering the "mouth" will end up passing out of any surface that is formed around the mouth

Goddard ECE329  
Lectures 12-14

21

## Example: Infinite Plane Sheet of Current



xz plane is an infinite sheet of current


Current density =  $J_s 0 \mathbf{a}_z (\text{A/m})$

Solve for flux density  $\mathbf{B}$

Goddard ECE329  
Lectures 12-14

22


## Step 1 - draw a picture



Goddard ECE329  
Lectures 12-14

23


## Step 2 - divide into segments



Goddard ECE329  
Lectures 12-14

24

### Step 3 - find $d\mathbf{B}$ for one small segment




At every point  $(x,y)$ , only the  $x$ -component remains, why?  
For  $y>0$ , it is in  $-\mathbf{a}_x$  direction

25

Goddard ECE329  
Lectures 12-14


### Step 4 – use symmetry to eliminate components that are zero



26

Goddard ECE329  
Lectures 12-14

Aha! Now that we know  $\mathbf{B}$  is along  $\mathbf{a}_x$ , we can apply Ampere's Law to a simple path



27

Goddard ECE329  
Lectures 12-14

And now for the math ...

$$\oint_C \frac{\vec{B}}{\mu_0} \cdot d\vec{l} = I \quad \Rightarrow \quad \frac{B}{\mu_0} L + \frac{B}{\mu_0} L = J_{s0} L$$

$$B = \frac{1}{2} \mu_0 J_{s0}$$

$$\vec{B} = \frac{1}{2} \mu_0 J_{s0} (\pm \hat{a}_x)$$

28

Goddard ECE329  
Lectures 12-14

### General Formula for $\mathbf{B}$ due to infinite current sheet

The direction of current flow can be in ANY direction  
The current sheet might not be on a coordinate plane

$$\mathbf{B} = \frac{\mu_0}{2} \vec{J}_s \times \hat{a}_n$$

↓  
Unit vector normal  
to the surface

29

Goddard ECE329  
Lectures 12-14

### Sample problem

- Infinite plane sheets of current lie in the  $x=0$ ,  $y=0$ , and  $z=0$  planes with uniform surface current densities  $J_{s0}\mathbf{a}_z$ ,  $2J_{s0}\mathbf{a}_x$ , and  $-J_{s0}\mathbf{a}_x$ , respectively. Find  $\mathbf{B}$  at the points: (a)  $(1,2,2)$ , (b)  $(2,-2,-1)$  and (c)  $(-2,1,-2)$ .

30

Goddard ECE329  
Lectures 12-14

Problem taken from D1.20 p58 in old book

## Lecture 12 Summary

- Ampere's Force Law  $d\vec{F}_1 = I_1 d\vec{l}_1 \times d\vec{B}_1$
- Biot-Savart Law  $d\vec{B}_{at\ 1} = \frac{\mu_0}{4\pi} \frac{I_2 d\vec{l}_2 \times \hat{a}_R}{R^2}$
- Infinite line of current  $\vec{B} = \frac{\mu_0 I}{2\pi r} \hat{a}_\phi$
- Lorentz Force Equation  $\vec{F}_{TOTAL} = q\vec{E} + q\vec{v} \times \vec{B}$
- Next class
  - Ampere's Law (Section 2.4)

Goddard ECE329  
Lectures 12-14

31

## Lecture 13 Section 2.4

### Ampere's Law Displacement Current

Adapted from Prof. Cunningham's Notes


Goddard ECE329  
Lectures 12-14

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

32

## "Static" Ampere's Law

Using the Biot-Savart Law, we solved for the B field around a straight wire:



$$\vec{B} = \frac{\mu_0 I}{2\pi r} \hat{a}_\phi$$

Magnetic flux density  
(Wb/m<sup>2</sup>)

33

Goddard ECE329  
Lectures 12-14

## "Static" Ampere's Law

We integrated B over any circular path centered on the wire:

$$\oint_C \vec{B} \bullet d\vec{l} = \int_{\phi=0}^{2\pi} \left( \frac{\mu_0 I}{2\pi r} \hat{a}_\phi \right) \bullet (r d\phi \hat{a}_\phi) \\ = \int_{\phi=0}^{2\pi} \left( \frac{\mu_0 I}{2\pi} \right) \\ = \mu_0 I$$

So...  $\oint_C \frac{\vec{B}}{\mu_0} \bullet d\vec{l} = I$  for any radius circle

34

Goddard ECE329  
Lectures 12-14

## Ampere's Law Physical Meaning

$$\oint_C \frac{\vec{B}}{\mu_0} \bullet d\vec{l} = I_{enclosed}$$

Taking the integral of the quantity  $(B/\mu_0)$  around a closed path equals the enclosed current.

$$\oint_C \frac{\vec{B}}{\mu_0} \bullet d\vec{l} = Magneto\ Motive\ Force\ (MMF)$$

similar to:

$$\oint_C \vec{E} \bullet d\vec{l} = Electro\ Motive\ Force\ (EMF)$$

**Caution: MMF does no work!**

35

Goddard ECE329  
Lectures 12-14

## New Definition: Magnetic Field Intensity Vector

$$\oint_C \frac{\vec{B}}{\mu_0} \bullet d\vec{l} = I_{enclosed}$$

$$\vec{H} = \frac{\vec{B}}{\mu_0}$$


Units: (A/m)

36

Goddard ECE329  
Lectures 12-14

## Static Ampere's Law

Open Surface, where the Path forms a "Mouth"



According to this static law, all the current entering the "mouth" will end up passing out of any surface that is formed around the mouth. Is this true?


37

Goddard ECE329  
Lectures 12-14

## Problem with Static Ampere's Law

Consider a simple capacitor

- No DC current goes through
- But, AC voltage results in current flow




How does AC current get through a capacitor if it is not conducted through by a wire?

38

Goddard ECE329  
Lectures 12-14

## Problem with Static Ampere's Law




There is a second "way" to get current to flow

Somehow, a TIME-VARYING E field results in current flow

39

Goddard ECE329  
Lectures 12-14

## Problem with Static Ampere's Law



Flux of E field lines crossing a surface, S

$$\psi_E = \oint_S \vec{E} \bullet d\vec{S}$$

Recall the Definition: Electric Flux  
Units: (C)

40


Goddard ECE329  
Lectures 12-14

## James Clerk Maxwell's Genius Breakthrough

There are TWO sources of MMF:

1. Flow of charges due to current
2. Time-varying electric field

Called (by Maxwell)  
"Displacement Current"



$$\oint_C \vec{H} \bullet d\vec{L} = \iint_S \vec{J} \bullet d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \bullet d\vec{S}$$

$$\text{MMF (Amps)} = \text{"Regular" Current (Amps)} + \text{Displacement Current (Amps)}$$

41

Goddard ECE329  
Lectures 12-14

## "New" Definition: Displacement Flux Density Vector

$\vec{E}$  "Electric Field Intensity Vector" V/m

$\vec{D} = \epsilon_0 \vec{E}$  "Displacement Flux Density Vector"

$$\text{Units: } \vec{D} = \frac{\text{Charge}}{\text{Area}} = \frac{C}{m^2}$$

$$\psi_E = \iint_S \epsilon_0 \vec{E} \bullet d\vec{S} = \iint_S \vec{D} \bullet d\vec{S} \text{ Coul}$$

$$\frac{d\psi_E}{dt} = \frac{d}{dt} \iint_S \vec{D} \bullet d\vec{S} \text{ Coul/sec (Amps)} \quad 42$$

Goddard ECE329  
Lectures 12-14

## Displacement current from a time varying E-field

- Find the displacement current crossing an area  $A=0.1\text{m}^2$  in the xy plane from the  $-z$  to  $+z$  side for:

$$\mathbf{E} = E_0 t e^{-t^2} \mathbf{a}_z$$

43

Goddard ECE329  
Lectures 12-14

From Discussion 2.8 (p 106) of old book

## Ampere's Law (Non static)

The Third Maxwell Equation

$$\oint_C \vec{H} \bullet d\vec{l} = \iint_S \vec{J} \bullet d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \bullet d\vec{S}$$

MMF = "Regular" Current (Amps) + Displacement Current (Amps)

$$\nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$$

After using Stokes' theorem to convert to differential form

44

Goddard ECE329  
Lectures 12-14


## Ampere's Law Rules

- Right Hand Rule:  
Choose direction of C so  $dS$  points OUT of the surface
- Must use same surface when evaluating surface integrals for conduction current and displacement current

45

Goddard ECE329  
Lectures 12-14

## Displacement Current



- The displacement current bridges the gap in the capacitor plates
  - Regular current flowing into the CLOSED surface = displacement current flowing out

$$-\iint_S \vec{J} \bullet d\vec{S} = \frac{d}{dt} \iint_S \vec{D} \bullet d\vec{S}$$

$$\boxed{\text{---}} = \boxed{\text{---}} + \boxed{\text{---}}$$

46

Goddard ECE329  
Lectures 12-14

## Displacement Current

- Current flow changes the amount of charge
  - Since the charge changes, the electric flux out of the surface changes, i.e. a displacement current

$$\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_r$$

$$\psi_E = \iint_S \epsilon_0 \vec{E} \bullet d\vec{S} = \epsilon_0 E (\text{Surf Area})$$

$$= \epsilon_0 \frac{Q}{4\pi\epsilon_0 R^2} (4\pi R^2) = Q$$

$$I_d = \frac{d\psi_E}{dt} = \frac{dQ}{dt}$$

$$I_d = \frac{dQ}{dt} = I_{in} \text{ because current out = current in}$$

47

Goddard ECE329  
Lectures 12-14

## Displacement Current from time varying charge

- 3 point charges,  $Q_1(t)$ ,  $Q_2(t)$ , and  $Q_3(t)$  are at the corners of an equilateral triangle and connected by wires. Currents of  $I$  and  $3I$  flow from  $Q_1$  to  $Q_2$  and  $Q_3$  respectively. The displacement current emanating from a small surface surrounding  $Q_2$  is  $-2I$ . Find: (a) the current flowing from  $Q_2$  to  $Q_3$  and (b) the displacement current from a small surface surrounding  $Q_1$  and surrounding  $Q_3$ .


48

Goddard ECE329  
Lectures 12-14

From Discussion 2.9 (p 106) of old book

## Challenge Question 1

- Current moves along a wire connecting two point charges. For which closed surface can the displacement current be non-zero?




49

Goddard ECE329  
Lectures 12-14

## Challenge Question 2

- Current moves along a wire connecting two point charges. For which infinite plane (open surface) can the displacement current be non-zero?



50

Goddard ECE329  
Lectures 12-14

## Lecture 13 Summary

- Ampere's Circuit Law
- Next class
  - Faraday's Law (Sections 2.1 and 2.3)

51

Goddard ECE329  
Lectures 12-14

## Lecture 14 Sections 2.1 and 2.3

### Review of Line Integrals Faraday's Law


Adapted from Prof. Cunningham's Notes

52

Goddard ECE329  
Lectures 12-14

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Work is a Line Integral



$$W_{AB} = \sum_{j=1}^n \vec{F}_j \cdot \vec{dL}_j = \int_A^B \vec{F} \cdot d\vec{L}$$

53

Goddard ECE329  
Lectures 12-14

## Conservative Forces

- Conservative means the work done by the force is independent of path
  - E.g. Gravity, Static Electric/Magnetic
- No work done along any closed loop
- Described by a potential energy
  - Energy conservation
    - Work done increases KE & decreases PE
    - Friction, Drag & Time Dependent Electric or Magnetic Forces are non-conservative
- Curl-free (non-rotational)
  - Field strength does not vary perpendicular to the field direction

54

Goddard ECE329  
Lectures 12-14

## The Force From a **Static** EM Field is Conservative

- Definition of Voltage

$$V_B - V_A = \frac{W_{AB}}{q} = - \sum_{j=1}^n \mathbf{E}_j \cdot \Delta \mathbf{l}_j$$

Voltage drop from  $B$  to  $A$  is equal to the work you need to do to move a unit charge from  $A$  to  $B$  against the electric field  $\mathbf{E}$ .

- In the limit  $n \rightarrow \infty$ ,


$$V_B - V_A = - \int_A^B \mathbf{E} \cdot d\mathbf{l}$$

= Line integral of  $E$  from  $A$  to  $B$ . Well defined since integral is independent of path.

55

Goddard ECE329  
Lectures 12-14

## Non-conservative Fields: Electromotive Force (emf)



$$emf = \oint_C \mathbf{E} \cdot d\mathbf{l}$$

= Line integral of  $E$  around the closed path  $C$  (counter-clockwise).

EMF can be non-zero if EM field varies in time.  
EMF is a difference in potential that can give rise to an electric current. Think of it as a battery between  $A$  and  $B$ .

56

Goddard ECE329  
Lectures 12-14

## Summary of Conservative Fields

- Conservative fields

– Line integral around a closed path is ZERO

– Gravity, static EM Field

- Non-conservative fields

– Line integral around a closed path is NONZERO

– Friction, time-varying EM Field

57

Goddard ECE329  
Lectures 12-14

## Faraday's Law

When the magnetic flux enclosed by a loop of wire CHANGES WITH TIME, a current is produced in the loop



The EMF in the loop is the NEGATIVE of the rate of change of the magnetic flux enclosed in the loop

$$\oint_C \vec{E} \cdot d\vec{l} = - \frac{d}{dt} \iint_S \vec{B} \cdot d\vec{S}$$

Our third Maxwell Equation!!!

$$emf = - \frac{d\psi_B}{dt}$$


58

Goddard ECE329  
Lectures 12-14

## Lenz's Law

- The direction of the induced EMF always OPPOSES the CHANGE in magnetic flux that produces it.

- It opposes the **CHANGE** in flux, not the flux itself!




– Explains why it is  $-d/dt$

59

Goddard ECE329  
Lectures 12-14

## The curve $C$ and surface $S$




Closed Path, **C**  
enclosing open  
surface **S<sub>1</sub>**

It also encloses  
open surface **S<sub>2</sub>**

- Outward magnetic flux thru the closed surface:  $S_1 \cup S_2$  is zero
  - The flux out any open surface  $S_2$  = minus the flux out  $S_1$  = plus the flux into  $S_1$  so all surfaces  $S$  bounded by  $C$  have the same flux

Goddard ECE329  
Lectures 12-14

## Faraday's Law Rules




- Right Hand Rule

– Right hand curls around C so thumb points in direction of  $d\mathbf{S}$

Goddard ECE329  
Lectures 12-14

61


## Experiments for Faraday's Law



Goddard ECE329  
Lectures 12-14

62

## Induced emf around rectangular loop in a time-varying $\mathbf{B}$ field



- Rectangular wire loop  
In the xz-plane  
 $\vec{B} = B_0 \cos \omega t \hat{a}_y$
- Steps:
1. Write down Faraday's law
  2. Write down expression for  $d\mathbf{S}$ . DIRECTION!!
  3. Perform dot product  $\mathbf{B} \cdot d\mathbf{S}$
  4. Solve double integral over limits of the loop
  5. Take time derivative of result. Put in “-” sign!

Goddard ECE329  
Lectures 12-14


## Faraday's Law Rules

- EMF increases in proportion to the number of turns of wire
  - If the loop, C, contains N turns of wire, the EMF is multiplied by N

$$EMF = -N \frac{d\psi_B}{dt}$$

64

## Example Problem: Induced emf around closed path




We can make the problem easier by solving for the flux going into the three surfaces on the coordinate planes

Goddard ECE329  
Lectures 12-14

From Discussion 2.5b p100 in old book

65



Steps

1. Identify surfaces on the coordinate axes that are bounded by the same closed path C
2. Solve for  $\iint \mathbf{B} \cdot d\mathbf{S}$  separately for each surface
3. Add up contribution of each surface for the final result

66

$\vec{B} = B_0(\sin \omega t \hat{a}_x - \cos \omega t \hat{a}_y)$

surface1      surface2  
surface3

Solving for  $\iint \vec{B} \cdot d\vec{S}$  of each component surface

1. Write down expression for  $dS$ . PAY ATTENTION TO DIRECTION!
2. Perform dot product with  $B$ . Is the dot product zero for a particular surface?
3. Shortcut if  $B$  is uniform over the surface. Then  $\iint_s \vec{B} \cdot d\vec{S} = (\text{Surface Area})(B)$
4. Otherwise, perform double integral over the dimension limits of the surface.

Goddard ECE329  
Lectures 12-14

67

### Example Problem: Motional EMF

- A non-uniform static magnetic field given by  $B=B_0/x \mathbf{a}_z$  exists in the region  $x>0$ . A square loop with side length,  $s$ , and situated in the  $xy$  plane ( $x>0$ ) moves in the  $+a_x$  direction with speed  $v$ . Find the induced emf in the loop.

68

Goddard ECE329  
Lectures 12-14

Adapted from Problem 2.11 (p 123) of old book

### Challenge Question

A loop, radius  $R$ , centered at the origin, sits in the  $xy$  plane in the presence of a uniform field  $\mathbf{B}=B_0 \mathbf{a}_z$  ( $B_0>0$ ). If the loop radius begins to decrease, which direction is the induced emf?

(a)  $\mathbf{a}_\phi$   
 (b)  $-\mathbf{a}_\phi$   
 (c)  $\mathbf{a}_z$   
 (d) cannot be determined

69

Goddard ECE329  
Lectures 12-14

### Comparing Faraday and Ampere's Law

- Faraday's Law
  - Time varying magnetic fields generate emf (voltage)
- Ampere's Law
  - Time varying electric fields generate magnetic fields
  - Electric currents generate magnetic fields (Ampere's static law)

70

Goddard ECE329  
Lectures 12-14

### EMF and MMF

$$\oint_c \vec{E} \cdot d\vec{l} = EMF$$

$$\oint_c \vec{H} \cdot d\vec{l} = MMF$$

$E = \text{Volts/m}$        $H = \text{Amps/m}$

$EMF = \text{Volts}$        $MMF = \text{Amps}$

71

Goddard ECE329  
Lectures 12-14

### Lecture 14 Summary

- Faraday's Law: \_\_\_\_\_
  - The generated emf opposes \_\_\_\_\_ and for a loop with  $N$  turns is \_\_\_\_\_ times larger
  - The direction for  $C$  and  $dS$  determined by right hand rule
- Next class
  - Magnetic Vector Potential (Section 10.6 – just pp. 406-407)
  - Inductance (Section 6.3)

72

Goddard ECE329  
Lectures 12-14

# ECE 329

## Lectures 15-17

### Sections 10.6, 6.3, 2.5, 5.5, 5.2

Magnetic Vector Potential  
Inductance  
Conservation of Charge (Continuity)  
Boundary Conditions  
Magnetic Materials

Goddard ECE329  
Lectures 15-17

Adapted from Prof. Cunningham's Notes  
1  
© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Magnetic Potentials

$$\vec{\nabla} \cdot \vec{B} = 0 \quad \text{Gauss' Law}$$

If the divergence is zero, then  $\mathbf{B}$  can be written as the curl of a vector (not obvious  $\mathbf{A}$  should exist, but it does)

New Definition: Magnetic Potential Vector

$$\vec{B} = \vec{\nabla} \times \vec{A}$$

Oddly familiar:

$$\vec{\nabla} \cdot (\vec{\nabla} \times \vec{A}) = 0$$

2

Goddard ECE329  
Lectures 15-17

## Faraday's Law

$$\vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t} = -\frac{\partial}{\partial t}(\vec{\nabla} \times \vec{A})$$

$$\vec{\nabla} \times \vec{E} = -\vec{\nabla} \times \frac{\partial \vec{A}}{\partial t}$$

$$\vec{\nabla} \times (\vec{E} + \frac{\partial \vec{A}}{\partial t}) = 0$$

If curl is zero, then can be written as the gradient of a scalar

Oddly familiar:

$$\vec{E} + \frac{\partial \vec{A}}{\partial t} = -\nabla \Phi$$

$$\vec{\nabla} \times \nabla \Phi = 0$$

3

Goddard ECE329  
Lectures 15-17

## Electric and Magnetic Potentials

$$\vec{E} = -\nabla \Phi - \frac{\partial \vec{A}}{\partial t}$$

Electric Magnetic  
Potential Potential

$$\vec{B} = \vec{\nabla} \times \vec{A}$$

With these definitions, we automatically satisfy Faraday's Law & Gauss' Magnetic Law

Instead of 6 unknowns: ( $E_x, E_y, E_z$ ) & ( $B_x, B_y, B_z$ ) we have 4: ( $A_x, A_y, A_z$ ) and  $V$

4


Goddard ECE329  
Lectures 15-17

## The magnetic potential $\mathbf{A}$ and its relations to $\mathbf{E}$ and $\mathbf{B}$

$$EMF = -\frac{d\psi_B}{dt} = -\frac{d}{dt} \iint_S \vec{B} \cdot d\vec{S}$$

$$= -\frac{d}{dt} \iint_S (\nabla \times \vec{A}) \cdot d\vec{S} = -\frac{d}{dt} \oint_C \vec{A} \cdot d\vec{l} = -\oint_C \frac{\partial \vec{A}}{\partial t} \cdot d\vec{l}$$

assuming the loop geometry is constant



$$EMF = \oint_C \vec{E} \cdot d\vec{l} = \oint_C (-\nabla \Phi - \frac{\partial \vec{A}}{\partial t}) \cdot d\vec{l} = -\oint_C \frac{\partial \vec{A}}{\partial t} \cdot d\vec{l}$$

why can we drop gradient of  $\Phi$ ?

5

Goddard ECE329  
Lectures 15-17

## Gauss' Electric Law for Potentials

$$\vec{\nabla} \cdot \vec{D} = \rho$$

$$\vec{\nabla} \cdot \epsilon \vec{E} = \rho$$

$$\vec{\nabla} \cdot \vec{E} = \frac{\rho}{\epsilon} \quad \text{Assuming } \epsilon \text{ is constant}$$

$$\vec{\nabla} \cdot \left( -\nabla \Phi - \frac{\partial \vec{A}}{\partial t} \right) = \frac{\rho}{\epsilon} \quad 1 \text{ equation}$$

6

Goddard ECE329  
Lectures 15-17

## Ampere's Law for Potentials

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{A}}{\partial t}$$

$$\vec{\nabla} \times \frac{\vec{B}}{\mu} = \vec{J} + \epsilon \frac{\partial \vec{E}}{\partial t}$$

$$\vec{\nabla} \times \vec{B} = \mu \vec{J} + \mu \epsilon \frac{\partial \vec{E}}{\partial t}$$

$$\vec{\nabla} \times \vec{B} - \mu \epsilon \frac{\partial \vec{E}}{\partial t} = \mu \vec{J}$$

$$\vec{\nabla} \times (\vec{\nabla} \times \vec{A}) - \mu \epsilon \frac{\partial}{\partial t} \left( -\nabla \Phi - \frac{\partial \vec{A}}{\partial t} \right) = \mu \vec{J}$$

3 equations

7

Goddard ECE329  
Lectures 15-17

## Special Case: Static Fields

Gauss

$$\vec{\nabla} \cdot \left( -\nabla \Phi - \frac{\partial \vec{A}}{\partial t} \right) = \frac{\rho}{\epsilon}$$

Ampere

$$\vec{\nabla} \times (\vec{\nabla} \times \vec{A}) - \mu \epsilon \frac{\partial}{\partial t} \left( -\nabla \Phi - \frac{\partial \vec{A}}{\partial t} \right) = \mu \vec{J}$$

$$\vec{\nabla} \cdot (\nabla \Phi) = -\frac{\rho}{\epsilon}$$

$$\vec{\nabla} \times (\vec{\nabla} \times \vec{A}) = \mu \vec{J}$$

We studied this one already (Poisson):  
Relationship between a charge distribution and the potential field

8

Goddard ECE329  
Lectures 15-17

## Challenge Question: Gauge Transformation

- Suppose  $\mathbf{E}$  and  $\mathbf{B}$  can be represented by the scalar and vector potentials:  $\Phi$  and  $\mathbf{A}$ .

$$\vec{E} = -\nabla \Phi - \frac{\partial \vec{A}}{\partial t}$$

$$\vec{B} = \vec{\nabla} \times \vec{A}$$

Which of the following is true:

- (a)  $\Phi$  and  $\mathbf{A}$  are uniquely defined
- (b)  $\vec{A} = \vec{A} + \nabla \lambda$ ,  $\Phi' = \Phi - \frac{\partial \lambda}{\partial t}$  also represents  $\mathbf{E}$  and  $\mathbf{B}$
- (c) The divergence of  $\mathbf{A}$  must be 0
- (d) The laplacian of  $\Phi$  must be  $-\rho/\epsilon$

9

Goddard ECE329  
Lectures 15-17

LG's question

## Lecture 15a Summary

- Since  $\text{div curl } \mathbf{A} = 0$  and  $\text{curl grad } f = 0$ ,

$$\vec{E} = -\nabla \Phi - \frac{\partial \vec{A}}{\partial t}$$

$$\vec{B} = \vec{\nabla} \times \vec{A}$$

satisfy Faraday's and Gauss' Mag. Laws

- For static fields, Poisson's equation is

$$\nabla^2 \Phi = -\frac{\rho}{\epsilon}$$

10

Goddard ECE329  
Lectures 15-17

## ECE 329 Lecture 15b Section 6.3

### Inductance


Adapted from Prof. Cunningham's Notes

11

Goddard ECE329  
Lectures 15-17

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited.


Example: Find  $\mathbf{B}$  for an infinitely long solenoid with  $n$  turns per unit length



12

Goddard ECE329  
Lectures 15-17

## Inductance of a Coax Cable



Now, instead of applying a voltage across the inner and outer conductor, a current,  $I$ , flows down the length of the outer conductor and returns in the opposite direction through the inner conductor

Results in magnetic field


$$H_\phi = \frac{I}{2\pi r}$$

in between the coax

13

Goddard ECE329  
Lectures 15-17

## Inductance of Coaxial Cable



$$\vec{B} = \mu \vec{H} = \frac{\mu I}{2\pi r} \vec{a}_\phi \quad \text{Magnetic Flux Density} \quad \left[ \frac{Wb}{m^2} \right]$$

$$\psi = \int B \cdot dS = \int_{r=a}^b \int_{z=0}^z \left( \frac{\mu I}{2\pi r} \right) (dr dz) \quad \text{Magnetic Flux} \quad [Wb]$$

$$\psi = \frac{\mu I z}{2\pi} \ln(b/a)$$

14

Goddard ECE329  
Lectures 15-17

## Inductance

$$L = \frac{\psi}{I} \quad \text{Units: Henry (H)}$$

$$L = \frac{\mu z}{2\pi} \ln(b/a)$$

$$L = \frac{L}{z} = \frac{\mu}{2\pi} \ln(b/a) \quad \text{Inductance/Length (H/m)}$$

15


Goddard ECE329  
Lectures 15-17

## Induced emf

Faraday's Law

$$emf = \oint \vec{E} \cdot d\vec{l} = -\frac{d\psi_B}{dt}$$

$$emf = -\frac{d(LI)}{dt} = -L \frac{dI}{dt}$$



Assuming  $dI/dt > 0$

The inductance of the wire creates an emf that opposes rapid changes in the current

16

Goddard ECE329  
Lectures 15-17

## Steps for Finding Inductance

- Find  $H(r)$
- Find  $B \quad \vec{B} = \mu \vec{H}$
- Find Magnetic flux by integrating  $\psi = \int B \cdot dS$
- Inductance  $L = \frac{\psi}{I}$
- Inductance/Length

17

Goddard ECE329  
Lectures 15-17

## Relationships between Capacitance, Conductance & Inductance

Notice in the above examples,

$$\mathcal{C} = \epsilon \cdot \text{GeometricalFactor}$$

$$\mathcal{G} = \sigma / \text{GeometricalFactor}$$

$$\mathcal{L} = \mu / \text{GeometricalFactor}$$

This is true in general for any pair of infinitely long, parallel perfect conductors and so we have the following:

$$\mathcal{LC} = \mu \epsilon \quad \mathcal{G/C} = \sigma / \epsilon$$

If you know one ( $L$ ,  $C$ , or  $G$ ), you can find the other two from the material parameters

18

Goddard ECE329  
Lectures 15-17

## Challenge Question: Parallel plate capacitor

- For the parallel plate capacitor, we found

$$\text{Diagram: } \begin{array}{c} d \\ | \\ \text{---} \\ | \\ \varepsilon \\ | \\ \text{---} \\ | \\ w \end{array} \quad V_0 \quad C = \frac{\varepsilon A}{d} \Rightarrow C = \frac{\varepsilon w}{d}$$

If the plate separation  $d$  increases, which is true:

- $\mathcal{G}$  and  $\mathcal{L}$  will both increase
- $\mathcal{C}$  and  $\mathcal{G}$  will both increase
- $\mathcal{L}$  will increase, but  $\mathcal{C}$  will decrease
- $\mathcal{G}$  will increase, but  $\mathcal{L}$  will decrease


19

Goddard ECE329  
Lectures 15-17


LG's question

## (Optional) Self Inductance

Last Example



New Example




There now is also  $H$  field inside the inner wire that will also contribute to inductance

20

Goddard ECE329  
Lectures 15-17

## (Optional) Self Inductance


Last Example



$$L = \frac{\psi}{I}$$

Goddard ECE329  
Lectures 15-17

New Example



$$L = \frac{\Lambda}{I} \rightarrow \text{"Flux Linkage"}$$

21

## (Optional) Flux Linkage

$$J_S = \frac{I}{\pi r_0^2}$$

This flux line is "linked" to a small amount of current

This flux line is "linked" to a large amount of current

AND, since flux  $\psi_B$  is dependent on  $r$

Flux here is LOW

Flux here is HIGH

22

Goddard ECE329  
Lectures 15-17

## (Optional) Definition of Flux Linkage

$$\Lambda = (\text{Flux Magnitude}) \cdot (\text{Fraction of Current Linked to the Flux Line})$$

Accounts for two factors:

- The magnitude of the flux line
- The amount of current linked to a flux line

The self inductance is then defined as:

$$L_{int} = \frac{\Lambda}{I_{total}} = \int_S \frac{d\Lambda}{I_{total}} = \int_S \frac{N \cdot d\psi}{I_{total}} = \frac{1}{I_{total}^2} \int_S I_{linked} d\psi$$

$$\text{Fraction of linked current: } N = \frac{I_{linked}}{I_{total}}$$

23

Goddard ECE329  
Lectures 15-17

## (Optional) Example: Self-Inductance of a Wire

Step 1: Ampere's Law inside the Wire

$$\oint \vec{H} \cdot d\ell = I_{enclosed}$$


$$\oint \frac{\vec{B}}{\mu} \cdot d\ell = I_{enclosed}$$

$$\frac{1}{\mu} \int_{\phi=0}^{2\pi} B_\phi (r d\phi) = I_{enclosed}$$

$$\frac{1}{\mu} B_\phi (2\pi r) = I_{enclosed}$$

$$\frac{1}{\mu} B_\phi (2\pi r) = J_s (\text{Area}_\text{Enclosed})$$

$$\frac{1}{\mu} B_\phi (2\pi r) = \left( \frac{I}{\pi r_0^2} \right) (\pi r^2) \quad (r < r_0)$$




Goddard ECE329  
Lectures 15-17

## (Optional) Example, continued

$$\frac{1}{\mu} B_\phi (2\pi r) = \left( \frac{I}{\pi r_0^2} \right) (\pi r^2) \quad (r < r_0)$$

$$B_\phi = \frac{\mu I}{2\pi r_0^2} r \quad (\text{Wb/m}^2)$$

Step 2: Determine One Differential Piece of Flux



$$d\psi_B = B(r) \cdot dr \cdot l \quad (\text{Wb})$$

25

Goddard ECE329  
Lectures 15-17

## (Optional) Example, continued

Step 3: Differential piece of flux linkage

$$d\Lambda = d\psi_B \cdot N$$

$$d\Lambda = d\psi_B \left( \frac{\pi r^2}{\pi r_0^2} \right) \quad \begin{matrix} \uparrow \\ N = \text{Fraction of current inside radius } r \end{matrix}$$

Step 4: Total flux linkage

$$\Lambda = \frac{\mu I \cdot l}{2\pi r_0^4} \int_0^{r_0} r^3 dr = \frac{\mu I \cdot l}{8\pi}$$

26

Goddard ECE329  
Lectures 15-17

## (Optional) Example, continued

Step 5: Internal inductance

$$L = \frac{\Lambda}{I} = \frac{\mu l}{8\pi} \quad (\text{units: Henry (H)})$$

Internal inductance per unit length of the wire:

$$\frac{L}{l} = \frac{\mu}{8\pi} \quad (\text{units: H/m})$$

27

Goddard ECE329  
Lectures 15-17

## Lecture 15b Summary

- Capacitance  $C = Q/V_0$
- Conductance  $G = |I_c|/V_0$
- Inductance  $L = \psi/I$
- Relationships  $\mathcal{LC} = \mu\epsilon$      $\mathcal{G}/\mathcal{C} = \sigma/\epsilon$
- Self-inductance  $L_{\text{int}} = \int_S \frac{Nd\psi}{I_{\text{total}}} = \int_S \frac{I_{\text{linked}}}{I_{\text{total}}^2} d\psi$
- Next Up
  - Conservation of Charge
  - Boundary Conditions

28

Goddard ECE329  
Lectures 15-17

## Lecture 16 Sections 2.5 and 5.5

Conservation of Charge  
Review of Maxwell's Equations in Integral Form  
Boundary Conditions

Adapted from Prof. Cunningham's Notes

29

Goddard ECE329  
Lectures 15-17

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited.

## Conservation of Charge

Say we have a container that can accumulate charge

Start pouring charges into the container

Flow of charges is a current,  $I$ , in Amps


If the charges don't leave the container the charge inside the container increases

Current flow IN = Charge INCREASE  
Current flow OUT = Charge DECREASE

30

Goddard ECE329  
Lectures 15-17

## Conservation of Charge



In general, we can pour charges in from more than one direction, or take some out from other parts of the container

$$\text{Net Rate of Current flow OUT} = \text{Net Rate of Charge DECREASE}$$

$$\iint_S \vec{J} \cdot d\vec{S} = -\frac{dQ_{enc}}{dt} = -\frac{d}{dt} \iiint_V \rho dV$$


$$\text{or, } \nabla \cdot \vec{J} = -\frac{\partial \rho}{\partial t} \quad \text{using the divergence theorem}$$

Goddard ECE329  
Lectures 15-17

31

## Conservation of Charge

Can be derived by combining two of Maxwell's equations



$$\begin{aligned} 0 &= \oint_{C_1} \vec{H} \cdot d\vec{l} + \oint_{C_2} \vec{H} \cdot d\vec{l} \\ &= \iint_{S_1} \vec{J} \cdot d\vec{S} + \frac{d}{dt} \iint_{S_1} \vec{D} \cdot d\vec{S} + \iint_{S_2} \vec{J} \cdot d\vec{S} + \frac{d}{dt} \iint_{S_2} \vec{D} \cdot d\vec{S} \\ &= \iint_S \vec{J} \cdot d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \cdot d\vec{S} \\ &= \iint_S \vec{J} \cdot d\vec{S} + \frac{d}{dt} \iiint_V \rho dV \end{aligned}$$

$$\therefore \iint_S \vec{J} \cdot d\vec{S} = -\frac{d}{dt} \iiint_V \rho dV = -\frac{dQ_{enc}}{dt}$$

32

Goddard ECE329  
Lectures 15-17

## Conservation of Charge

Differential equation derivation is much faster!

$$0 = \nabla \cdot (\nabla \times \vec{H}) = \nabla \cdot \left( J + \frac{\partial \vec{D}}{\partial t} \right) = \nabla \cdot J + \frac{\partial (\nabla \cdot \vec{D})}{\partial t} = \nabla \cdot J + \frac{\partial \rho}{\partial t}$$


$$\therefore \nabla \cdot J = -\frac{\partial \rho}{\partial t}$$

Goddard ECE329  
Lectures 15-17

33

## Application of multiple Maxwell's Equations

- Current I flows from a point charge  $Q(t)$  at the origin along the z-axis off to infinity. Find the counterclockwise MMF for a circular path of radius  $a$  in the xy plane centered at the origin.  
Hint: consider a sphere and a hemisphere



Goddard ECE329  
Lectures 15-17

From Example 2.5 (p 111) of old book

34

## Application of charge conservation


- For  $\mathbf{J} = < x, y, z >$ , find the rate of decrease of charge contained in the unit cube: corner vertices  $(0,0,0)$  and  $(1,1,1)$ .

Goddard ECE329  
Lectures 15-17


From Problem 2.24a (p 126) of old book

35

## E and B for basic configurations



$$\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_R$$




$$\vec{E} = \frac{\rho_I}{2\pi\epsilon_0 r} \hat{a}_r$$



$$\vec{E} = \frac{\rho_{so}}{2\epsilon_0} (\pm \hat{a}_z)$$



$$\vec{B}_\phi = \frac{\mu_0 I}{2\pi R}$$



$$B = \frac{\mu_0}{2} \bar{J}_s \times \hat{a}_n$$

Goddard ECE329  
Lectures 15-17

## Lecture 16a Summary

- Maxwell's Equations

-Gauss Magnetic: \_\_\_\_\_

-Gauss Electric: \_\_\_\_\_

-Faraday: \_\_\_\_\_

-Ampere + Maxwell:

37

Goddard ECE329  
Lectures 15-17

## Lecture 16b Sections 5.5

### Boundary Conditions

Adapted from Prof. Cunningham's Notes

38

Goddard ECE329  
Lectures 15-17

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Maxwell's Eqns - Integral form

$$\oint_c \vec{E} \bullet d\vec{l} = - \frac{d}{dt} \iint_s \vec{B} \bullet d\vec{S}$$

$$\oint_c \vec{H} \bullet d\vec{l} = \iint_s \vec{J} \bullet d\vec{S} + \frac{d}{dt} \iint_s \vec{D} \bullet d\vec{S}$$

$$\iint_s \vec{B} \bullet d\vec{S} = 0$$


$$\iint_s \vec{D} \bullet d\vec{S} = \iiint_v \rho dV$$

They are valid for ALL closed paths and closed surfaces, EVEN WHEN THEY SPAN A BOUNDARY BETWEEN TWO MATERIALS

39

Goddard ECE329  
Lectures 15-17

## Closed Path Through a Boundary




Closed path: abcd

Apply Faraday's Law and Ampere's Law to the closed path

40

Goddard ECE329  
Lectures 15-17

## Normal Vectors



$\hat{a}_n$  Vector NORMAL to the boundary. Points INTO medium 1


$\hat{a}_s$  Vector normal to the path, TANGENT to the interface.  
Use right hand rule for path to define direction

41

Goddard ECE329  
Lectures 15-17

## Faraday's Law at Boundary

$$\oint_c \vec{E} \bullet d\vec{l} = - \frac{d}{dt} \iint_s \vec{B} \bullet d\vec{S} = 0$$




Take limit as ad and bc go to zero  
Consider remaining E₁ and E₂ TANGENT TO SURFACE

$E_1 = E_2$  i.e.  $E_t$  is continuous

42

Goddard ECE329  
Lectures 15-17

## The closed path can enclose surface current



Example:


1. Current on surface of a conductor

43

Goddard ECE329  
Lectures 15-17

## Ampere's Law at Boundary


$$\oint_C \vec{H} \cdot d\vec{l} = \iint_S \vec{J} \cdot d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \cdot d\vec{S} = I_{\text{enclosed}}$$



Take limit as ad and bc go to zero  
Consider remaining H<sub>1</sub> and H<sub>2</sub> TANGENT TO SURFACE

$H_1 - H_2 = J_s$  i.e.  $H_i$  is discontinuous because of  $J_s$

$$(\vec{H}_1 - \vec{H}_2)_t = \vec{J}_s \times \hat{a}_n$$




$$\hat{a}_n \times (\vec{H}_1 - \vec{H}_2)_t = \vec{J}_s$$

Note: we know nothing about  $\hat{a}_n$

44

Goddard ECE329  
Lectures 15-17

## Closed surface through the volume




Medium 1 (above)  
 $\sigma_1, \epsilon_1, \mu_1$   
Medium 2 (below)  
 $\sigma_2, \epsilon_2, \mu_2$

45

Goddard ECE329  
Lectures 15-17

## The closed volume can enclose surface charges



Medium 1 (above)  
 $\sigma_1, \epsilon_1, \mu_1$   
Medium 2 (below)  
 $\sigma_2, \epsilon_2, \mu_2$

Example


1. Free charges on the surface of a conductor

46

Goddard ECE329  
Lectures 15-17

## Gauss' Law for D at Boundary

$$\iint_S \vec{D} \cdot d\vec{S} = \iiint_V \rho dV$$



Take limit as ae, bf, cg, and dh go to zero  
Consider D<sub>1</sub> and D<sub>2</sub> NORMAL TO SURFACE

$D_1 - D_2 = \rho$  i.e.  $D_n$  is discontinuous because of  $\rho_s$

47

Goddard ECE329  
Lectures 15-17

## Finding surface charge


- Given D on the surface of a perfect conductor, find the surface charge,  $\rho$ , at that point (Hint: what is the vector  $a_n$  for each surface):
  - $D = D_0 <1, -2, 2>$  pointing away from surface
  - $D = D_0 <1, 0, \sqrt{3}>$  pointing towards surface
  - $D = D_0 <0.8, 0, 0.6>$  pointing away

48

Goddard ECE329  
Lectures 15-17

From D4.13 (p262) of old book

## Gauss' Law for B at Boundary



Take limit as  $ae$ ,  $bf$ ,  $cg$ , and  $dh$  go to zero  
Consider  $B_1$  and  $B_2$  NORMAL TO SURFACE

$B_1 = B_2$  i.e.  $B_n$  is continuous

49

Goddard ECE329  
Lectures 15-17

## Challenge Question: Boundary conditions

- Which of the following are realizable as the field outside a perfect conductor




- 1, 2, and 3 can be either  $\mathbf{E}$  or  $\mathbf{H}$
- 1 can be either  $\mathbf{E}$  or  $\mathbf{H}$ , but 2 is  $\mathbf{E}$ , 3 is  $\mathbf{H}$
- 1 can be either  $\mathbf{E}$  or  $\mathbf{H}$ , but 2 is  $\mathbf{H}$ , 3 is  $\mathbf{E}$
- 1 can be neither  $\mathbf{E}$  nor  $\mathbf{H}$ , but 2 is  $\mathbf{E}$ , 3 is  $\mathbf{H}$
- 1 can be neither  $\mathbf{E}$  nor  $\mathbf{H}$ , but 2 is  $\mathbf{H}$ , 3 is  $\mathbf{E}$

50

Goddard ECE329  
Lectures 15-17

LG's question


## Remember this drawing!!



51

Goddard ECE329  
Lectures 15-17


## Boundary between Two Perfect Dielectrics



52

Goddard ECE329  
Lectures 15-17

## Surface of Perfect Conductor



53

Goddard ECE329  
Lectures 15-17

## (Time permitting) BCs for a rectangular cavity resonator

- The region  $0 < x < a$ ,  $0 < y < b$ ,  $0 < z < d$  is a perfect dielectric  $\epsilon = 4\epsilon_0$  and the boundary is a perfect conductor on all 6 sides. Inside the resonator, the fields are:

$$\vec{E} = E_0 \sin \frac{\pi x}{a} \sin \frac{\pi z}{d} \cos \omega t \hat{a}_y$$

$$\vec{H} = H_{01} \sin \frac{\pi x}{a} \cos \frac{\pi z}{d} \sin \omega t \hat{a}_x - H_{02} \cos \frac{\pi x}{a} \sin \frac{\pi z}{d} \sin \omega t \hat{a}_z$$

Find  $\rho_s$  and  $J_s$  on all 6 walls.


54

Goddard ECE329  
Lectures 15-17

From P4.29 (p277) of old book

## Lecture 16b Summary

- Never use the differential form of Maxwell's equations at a boundary – only use integral form



Goddard ECE329  
Lectures 15-17


## ECE 329 Lecture 17 Section 5.2

### Magnetic Materials

Adapted from Prof. Cunningham's Notes

56


## Magnetic Moments at the atomic scale



Internal magnetic fields are produced by electrons orbiting the nucleus,  $L$ , or by the internal spin of electrons,  $S$ . The atom has a magnetic dipole moment,  $m$

Goddard ECE329  
Lectures 15-17


## Net magnetic moment



A volume of material contains many magnetic moments. They might be randomly oriented.


58

## External $\mathbf{B}$ -field can rotate Magnetic Moments or change Orbital Velocity



Goddard ECE329  
Lectures 15-17

## Net magnetic moment



So after momentarily applying an external field, they can get magnetized and are mostly aligned in one direction. The internal field can keep them aligned to each other

60

## Magnetization Vector

$$\vec{M} = N\vec{m}$$

Magnetic dipole moment per unit volume

$N$  = # atoms per unit volume

$\vec{m}$  = average dipole moment per molecule

Units for  $\vec{M}$ :  $(1/m^3)$  ( $A \cdot m^2$ ) =  $A/m$

$$\vec{B}_{int} = \mu_0 \vec{M}$$

is the magnetic flux per unit area from the dipoles

61

Goddard ECE329  
Lectures 15-17

## Magnetic Susceptibility

$\mathbf{B}$  INSIDE the material is a function of how strong and how well-aligned all the magnetic moments are

The INTERNAL magnetic flux is INDUCED by the application of an EXTERNAL magnetic field

Total flux = Applied + Secondary

$$\vec{B}_{total} = \mu_0 (\vec{H}_{ext} + \vec{M})$$

Some materials are more easily "magnetized" than others

$$\vec{M} = \chi_m \vec{H}_{ext}$$

Definition of magnetic susceptibility (has no units) 62

Goddard ECE329  
Lectures 15-17

## Relative Magnetic Permeability

$$\vec{B}_{total} = \mu_0 (\vec{H}_{ext} + \vec{M})$$

$$\vec{M} = \chi_m \vec{H}_{ext}$$

$$\vec{D} = \epsilon_0 \vec{E}_{tot} + \vec{P}$$

$$\vec{P} = \epsilon_0 \chi_e \vec{E}_{tot}$$

$$\vec{B}_{total} = \mu_0 (1 + \chi_m) \vec{H}_{ext}$$

$$\vec{B} = \mu \vec{H}$$

$$\mu = \mu_0 (1 + \chi_m) = \mu_0 \mu_r$$

$$\mu_r = 1 + \chi_m$$

$$\vec{D} = \epsilon_0 (1 + \chi_e) \vec{E}_{tot}$$

$$\vec{D} = \epsilon \vec{E}_{tot}$$

$$\epsilon = \epsilon_0 (1 + \chi_e) = \epsilon_0 \epsilon_r$$

$$\epsilon_r = 1 + \chi_e$$

63

Goddard ECE329  
Lectures 15-17

## Diamagnetic Materials ( $\chi_m < 0$ )

- With  $\mathbf{H}_{ext}$ , the electron orbital speed changes depending on the relative orientation of  $\mathbf{v}$  and  $\mathbf{H}_{ext}$ 
  - Equivalent to a weak magnetic dipole that OPPOSES  $\mathbf{H}_{ext}$
- Magnetic susceptibility is a NEGATIVE number

Examples:

|        |                                 |
|--------|---------------------------------|
| Copper | $\chi_m = -0.94 \times 10^{-5}$ |
| Lead   | $\chi_m = -1.70 \times 10^{-5}$ |
| Water  | $\chi_m = -0.88 \times 10^{-5}$ |

64

Goddard ECE329  
Lectures 15-17

## Paramagnetic Materials ( $\chi_m > 0$ )

### Positive susceptibility

- With no  $\mathbf{H}_{ext}$ , domains of orbital electrons and spinning electrons exist
- However, the domains are physically oriented in random directions (as a function of time), so overall  $\mathbf{B}_{int} = 0$
- With  $\mathbf{H}_{ext}$ , domains reorient themselves to generate  $\mathbf{B}_{int}$  that ALIGNS WITH  $\mathbf{H}_{ext}$
- Magnetic susceptibility is a POSITIVE number

Examples:

|               |                                 |
|---------------|---------------------------------|
| Platinum      | $\chi_m = +2.90 \times 10^{-5}$ |
| Aluminum      | $\chi_m = +2.10 \times 10^{-5}$ |
| Liquid Oxygen | $\chi_m = +3.50 \times 10^{-5}$ |

65

Goddard ECE329  
Lectures 15-17

## Ferromagnetic Materials ( $\chi_m > 1$ )

- Very high susceptibility
- Microscopic "domains" that have strongly oriented magnetic dipoles
- Direction of magnetic dipole differs from one domain to another
- Under an externally applied  $H$  field, the domains can orient coherently (i.e. in the same direction)
- Using a strong enough applied field, the domain orientation can become permanent



Goddard ECE329  
Lectures 15-17

66

| Material                             |               | $\mu_r = 1 + \chi_m$ |
|--------------------------------------|---------------|----------------------|
| Bismuth                              | Diamagnetic   | 0.99983              |
| Silver                               | Diamagnetic   | 0.99993              |
| Lead                                 | Diamagnetic   | 0.99993              |
| Copper                               | Diamagnetic   | 0.99991              |
| Water                                | Diamagnetic   | 0.99991              |
| Vacuum                               | Nonmagnetic   | 1†                   |
| Air                                  | Paramagnetic  | 1.00000              |
| Aluminum                             | Paramagnetic  | 1.00002              |
| Palladium                            | Paramagnetic  | 1.0008               |
| 2-81 Permalloy powder (2 Mo, 81 Ni)‡ | Ferromagnetic | 130                  |
| Cobalt                               | Ferromagnetic | 250                  |
| Nickel                               | Ferromagnetic | 600                  |
| Ferroxcube 3 (Mn-An-ferrite powder)  | Ferromagnetic | 1,500                |
| Mild steel (0.2 C)                   | Ferromagnetic | 2,000                |
| Iron (0.2 impurity)                  | Ferromagnetic | 5,000                |
| Silicon Iron (4 Si)                  | Ferromagnetic | 7,000                |
| 78 Permalloy (78.5 Ni)               | Ferromagnetic | 100,000              |
| Mumetal (75 Ni, 5 Cu, 2 Cr)          | Ferromagnetic | 100,000              |
| Purified iron (0.05 impurity)        | Ferromagnetic | 200,000              |
| Superalloy (5 Mo, 79 Ni)§            | Ferromagnetic | 1,000,000            |

Goddard ECE  
Lectures 15-17

67

†By definition.

‡Percentage composition. Remainder is iron and impurities.

§Used in transformer applications with continuous tape-wound (gapless) cores.

## Magnetization

- An infinite plane ferromagnetic slab ( $\mu_r=100$ ) lies between two infinite plane sheets of uniform current density of  $J=\pm 0.1\hat{a}_y$  A/m. Find  $H$ ,  $B$ , and  $M$  inside the slab and compare to if the slab were non-magnetic ( $\mu_r=1$ ).



Goddard ECE329  
Lectures 15-17

From D4.6 (p238) of old book

68

$$\text{Hint: } H=(J/2)x\hat{a}_y = -(J/2)\hat{a}_x$$

$$H=(J/2)x\hat{a}_y = (J/2)\hat{a}_x$$

## Magnetization Current

Due to the spatial variation of magnetic dipole moments

$$M_y(z) = \frac{m_y}{\text{Volume}} = \frac{IA}{\text{Volume}} = \frac{I_{1x}(dx dz)}{dxdydz} = \frac{I_{1x}}{dy} \quad M_y(z+dz) = \frac{-I_{2x}}{dy}$$

$$I_{tot} = I_{1x} + I_{2x} = (M_y(z) - M_y(z+dz))dy$$

$$J_M = \frac{I_{tot}}{dy dz} = -\frac{\partial M_y}{\partial z} \hat{a}_z \quad \vec{J}_M = \vec{\nabla} \times \vec{M}$$

Goddard ECE329  
Lectures 15-17

69

## Ampere's Law in Mag. Material

$$\vec{\nabla} \times \left( \frac{\vec{B}}{\mu_0} \right) = \vec{J} + \vec{J}_M + \frac{\partial \vec{D}}{\partial t}$$

In magnetic medium, we need to include  $J_M$  with the total current

$$\vec{\nabla} \times \left( \frac{\vec{B}}{\mu_0} \right) = \vec{J} + \vec{\nabla} \times \vec{M} + \frac{\partial \vec{D}}{\partial t}$$

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$$

$$H \equiv \frac{\vec{B}}{\mu_0} - \vec{M}$$

$$\vec{B} = \mu_0(\vec{H} + \vec{M})$$

70

Goddard ECE329  
Lectures 15-17

## 3 types of materials

| Conductors  | Dielectrics  | Magnetic  |
|---|--|---|
|   |  |   |
| <b>Free electrons</b>   | <b>Polarized atoms/molecules</b><br><b>Bound electrons</b>   | <b>Magnetic moments</b><br><b>Bound electrons</b>                       |
| $E=0$ inside<br>$\rho=0$ inside<br>$\rho=p_0$ only surface charge<br>$V$ is same throughout<br>$E_{\text{outside}}$ is $\perp$ to surface | $E \neq 0$ inside but it is reduced<br>$E_{\text{tot}} = E_a + E_s$<br>$D = \epsilon E_{\text{tot}} = P + \epsilon_0 E_{\text{tot}}$ | $B_{\text{tot}} = B_a + B_s$<br>$B_{\text{tot}} = \mu H = \mu_0(H + M)$ |

Goddard ECE329  
Lectures 15-17

71

## Lecture 17 Summary

- Magnetic dipole moment  $\mathbf{m} = IA$
- Magnetization or magnetic dipole moment per unit volume  
$$\mathbf{M} = N\mathbf{m} = \chi_m \mathbf{H}_{\text{external}}$$
  - Simple linear isotropic magnetic material
    - Strengthens  $\mathbf{B}$ -field strength by  $(1+\chi_m)$
    - $\mathbf{H}$  has same value as free space
  - Magnetization current  $J_M = \nabla \times \mathbf{M}$
  - New definition  $\mathbf{H} = \mathbf{B}/\mu_0 - \mathbf{M}$  and  $\mathbf{B} = \mu \mathbf{H}$
- Upcoming schedule: Plane Waves
  - Sections 4.1, 4.2, 4.4, 4.5, 5.3, and 5.4

72

Goddard ECE329  
Lectures 15-17

## Lectures 18-20

### Sections 4.1, 4.2, 4.4, 4.5

### Section 4.6

### Uniform Plane Waves in Free Space

### Poynting's Theorem

Adapted from Prof. Cunningham's Notes

1

Goddard ECE329

Lectures 18-20

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

### Summary of Maxwell's Equations

$$\text{Faraday's Law} \quad \oint_c \vec{E} \bullet d\vec{l} = -\frac{d}{dt} \iint_s \vec{B} \bullet d\vec{S} \quad \nabla \times \vec{E} = -\frac{d\vec{B}}{dt}$$

$$\text{Ampere's Law} \quad \oint_c \vec{H} \bullet d\vec{l} = \iint_s \vec{J} \bullet d\vec{S} + \frac{d}{dt} \iint_s \vec{D} \bullet d\vec{S} \quad \nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$$

$$\text{Gauss' Law} \quad \iint_s \vec{B} \bullet d\vec{S} = 0 \quad \nabla \bullet \vec{B} = 0$$

$$\text{Gauss' Law} \quad \iint_s \vec{D} \bullet d\vec{S} = \iiint_V \rho dV \quad \nabla \bullet \vec{D} = \rho$$

$$\text{Continuity Eq.} \quad \iint_s \vec{J} \bullet d\vec{S} = -\frac{d}{dt} \iiint_V \rho dV \quad \nabla \bullet \vec{J} = -\frac{d\rho}{dt}$$

Goddard ECE329

Lectures 18-20

2

### Motivation for Waves

- Maxwell's equations say...

- Time variation in  $\mathbf{J}(t)$  leads to spatial variation of  $\mathbf{H}(t)$

$$\nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$$

- Time variation in  $\mathbf{H}(t)$  leads to spatial variation in  $\mathbf{E}(t)$

$$\nabla \times \vec{E} = -\frac{d\vec{B}}{dt}$$

- Time variation in  $\mathbf{E}(t)$  leads to spatial variation in  $\mathbf{H}(t)$

$$\nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$$

- This recursion relationship between  $\mathbf{E}(t)$  and  $\mathbf{H}(t)$  leads to electromagnetic wave propagation


3

Goddard ECE329

Lectures 18-20


### Field Source

- Infinite plane sheet of current at  $z=0$



4

Which direction do we expect the generated fields to point?



5

Goddard ECE329

Lectures 18-20

Hmm, we did the static case

$$\vec{H} = \frac{\vec{B}}{\mu_0} = \frac{1}{2} \vec{J} \times \hat{a}_n$$

$$\vec{H} = \frac{\vec{B}}{\mu_0} = \frac{1}{2} \vec{J} \times \hat{a}_n$$

$\vec{J}_s$

$d\vec{S}$


$\vec{H}$  direction:  
 $\perp \vec{J}_s$  and  $\perp d\vec{S}$

6

Goddard ECE329


Lectures 18-20

So we expect  $\mathbf{H}$  to be along the  $\pm y$ -direction




Goddard ECE329  
Lectures 18-20

$H_y$  only depends on  $z$  and  $t$



8

$\mathbf{E}$  depends only on  $z$  and  $t$ , but in what direction is  $\mathbf{E}$ ?



Goddard ECE329  
Lectures 18-20

$E_x \neq 0$ , what about  $E_y$  and  $E_z$ ?

$$0 = -\frac{dB_z}{dt} = (\nabla \times \vec{E})_z = \frac{\partial E_x}{\partial y} - \frac{\partial E_y}{\partial z}$$

So  $\frac{\partial E_x}{\partial z} = 0 \Rightarrow E_y = \text{const}$ , but const = 0 since we can turn off our source, i.e. set  $J(t) = 0$ .

$$0 = -\frac{dB_z}{dt} = (\nabla \times \vec{E})_z = \frac{\partial E_x}{\partial x} - \frac{\partial E_z}{\partial y}$$


No new information.

$$0 = \frac{\rho}{\epsilon_0} = \nabla \cdot \vec{E} = \frac{\partial E_x}{\partial x} + \frac{\partial E_y}{\partial y} + \frac{\partial E_z}{\partial z}$$

So  $\frac{\partial E_z}{\partial z} = 0 \Rightarrow E_z = \text{const} = 0$

10


$\mathbf{E}$  then must be along the  $x$ -direction



Goddard ECE329  
Lectures 18-20

Summary so far ...

- We have  $\mathbf{E}$  and  $\mathbf{H}$  that are
  - Perpendicular to each other
  - Perpendicular to the direction of propagation
  - Magnitude is constant ("uniform") in any plane perpendicular to the propagation direction



12

## Following Maxwell's Footsteps

- We will SIMULTANEOUSLY solve Maxwell's equations to find  $\mathbf{E}$  and  $\mathbf{H}$  caused  $\mathbf{J}$

$$\begin{aligned}\vec{\nabla} \times \vec{E} &= -\frac{\partial \vec{B}}{\partial t} & \vec{E} &= E_x(z,t) \vec{a}_x \\ \vec{\nabla} \times \vec{H} &= \vec{J} + \frac{\partial \vec{D}}{\partial t} & \vec{H} &= H_y(z,t) \vec{a}_y \\ \vec{J}_s &= -J_x(t) \vec{a}_x\end{aligned}$$

13

Goddard ECE329  
Lectures 18-20

## Apply the two Maxwell's Equations

- Performing the cross product, only two equations contain  $E_x$  or  $H_y$

$$\begin{aligned}\frac{\partial E_x}{\partial z} &= -\frac{\partial B_y}{\partial t} \\ \frac{\partial H_y}{\partial z} &= -J_x - \frac{\partial D_x}{\partial t}\end{aligned}$$

14

Goddard ECE329  
Lectures 18-20

## Simplify to $\mathbf{E}$ and $\mathbf{H}$

- Use constitutive relationships  $D = \epsilon_0 E$  and  $B = \mu_0 H$  for free space to express  $D$  and  $B$  in terms of  $E$  and  $H$
- We write the equations for everywhere EXCEPT at  $z=0$  (where the current source is) so  $J_x$  goes away - for now

$$\frac{\partial E_x}{\partial z} = -\frac{\partial B_y}{\partial t} = -\mu_0 \frac{\partial H_y}{\partial t}$$

$$\frac{\partial H_y}{\partial z} = -\frac{\partial D_x}{\partial t} = -\epsilon_0 \frac{\partial E_x}{\partial t}$$

15

Goddard ECE329  
Lectures 18-20

## Eliminate $\mathbf{H}$ in favor of $\mathbf{E}$ only

$$\begin{aligned}\frac{\partial E_x}{\partial z} &= -\mu_0 \frac{\partial H_y}{\partial t} \\ \frac{\partial H_y}{\partial z} &= -\epsilon_0 \frac{\partial E_x}{\partial t} \\ \frac{\partial^2 E_x}{\partial z^2} &= -\mu_0 \frac{\partial}{\partial z} \left( \frac{\partial H_y}{\partial t} \right) = -\mu_0 \frac{\partial}{\partial t} \left( \frac{\partial H_y}{\partial z} \right) = -\mu_0 \frac{\partial}{\partial t} \left( -\epsilon_0 \frac{\partial E_x}{\partial t} \right)\end{aligned}$$

- Coupled 1<sup>st</sup> order partial differential equation (PDE)  $\rightarrow$  single 2<sup>nd</sup> order PDE

16

Goddard ECE329  
Lectures 18-20

## This is the “wave equation”

$$\frac{\partial^2 E_x}{\partial z^2} = \mu_0 \epsilon_0 \frac{\partial^2 E_x}{\partial t^2}$$

- Why is it called a wave equation?
  - The solution to this differential equation will be a function whose shape moves like a wave in the  $z$ -direction
  - How do we solve it?
    - Two techniques: Separation of variables (see book) or factorable operators (my notes)
  - We will do the solution for  $\mathbf{E}$ , and then we can come back and plug the solution into Maxwell's equation to get  $\mathbf{H}$

17

Goddard ECE329  
Lectures 18-20

## Change of variables

- Makes the math a little cleaner

$$\tau = z \sqrt{\mu_0 \epsilon_0} \quad \text{Has units of time}$$

$$\frac{\partial^2 E_x}{\partial \tau^2} = \frac{\partial^2 E_x}{\partial z^2} \quad \text{Still the wave eqn}$$

18

Goddard ECE329  
Lectures 18-20

## Two possible solutions

$$\frac{\partial^2 E_x}{\partial \tau^2} = \frac{\partial^2 E_x}{\partial z^2}$$

$$\frac{\partial^2 E_x}{\partial \tau^2} - \frac{\partial^2 E_x}{\partial z^2} = 0$$

" $x^2 - y^2 = (x+y)(x-y)$ "

$$\left( \frac{\partial}{\partial \tau} + \frac{\partial}{\partial z} \right) \left( \frac{\partial}{\partial \tau} - \frac{\partial}{\partial z} \right) E_x = 0$$

$$\frac{\partial E_x}{\partial \tau} = -\frac{\partial E_x}{\partial z} \quad \frac{\partial E_x}{\partial \tau} = +\frac{\partial E_x}{\partial z}$$

Now we have two first order diff eqns that each can be a solution to the wave equation

19

Goddard ECE329  
Lectures 18-20

## Two possible solutions

$$\frac{\partial E_x}{\partial \tau} = -\frac{\partial E_x}{\partial z}$$

$$\frac{\partial E_x}{\partial \tau} = +\frac{\partial E_x}{\partial z}$$

If  $E_x$  is a function of  $(t-\tau)$   
the equation is satisfied

If  $E_x$  is a function of  $(t+\tau)$   
the equation is satisfied

$$E_x(\tau, t) = Af(t - \tau)$$

$$E_x(\tau, t) = Bg(t + \tau)$$

A = a constant

B = a constant

Combining the two possible solutions...

$$E_x(\tau, t) = Af(t - \tau) + Bg(t + \tau)$$

20

Goddard ECE329  
Lectures 18-20

## Changing variables back to $z$

$$E_x(\tau, t) = Af(t - \tau) + Bg(t + \tau)$$

$$E_x(z, t) = \underbrace{Af(t - z\sqrt{\mu_0\epsilon_0})}_{\text{Traveling wave propagating in the } +z \text{ direction}} + \underbrace{Bg(t + z\sqrt{\mu_0\epsilon_0})}_{\text{Traveling wave propagating in the } -z \text{ direction}}$$

Traveling wave propagating in the  $+z$  direction

Traveling wave propagating in the  $-z$  direction

21

Goddard ECE329  
Lectures 18-20

## Solving for $\mathbf{H}$

$$E_x(z, t) = Af(t - z\sqrt{\mu_0\epsilon_0}) + Bg(t + z\sqrt{\mu_0\epsilon_0})$$

$$\text{Recall...} \quad \frac{\partial \mathbf{H}_y}{\partial z} = -\epsilon_0 \frac{\partial \mathbf{E}_x}{\partial z}$$

$$H_y(z, t) = \frac{1}{\sqrt{\mu_0/\epsilon_0}} [Af(t - z\sqrt{\mu_0\epsilon_0}) - Bg(t + z\sqrt{\mu_0\epsilon_0})]$$

22

Goddard ECE329  
Lectures 18-20

## Two definitions

$$v_p = c = \frac{1}{\sqrt{\mu_0\epsilon_0}} = \text{speed of light} = 3 \times 10^8 \text{ (m/s)}$$

$$\eta_0 = \sqrt{\frac{\mu_0}{\epsilon_0}} \approx 377 \text{ (ohms)} \quad \text{Intrinsic impedance of free space}$$

23

Goddard ECE329  
Lectures 18-20

## Rewriting the solution

$$E_x(z, t) = Af(t - \frac{z}{v_p}) + Bg(t + \frac{z}{v_p})$$

$$H_y(z, t) = \frac{1}{\eta_0} \left[ Af(t - \frac{z}{v_p}) - Bg(t + \frac{z}{v_p}) \right]$$

Solution is a superposition of traveling waves

- one going in  $+z$  direction
- one going in  $-z$  direction

24

Goddard ECE329  
Lectures 18-20

## Challenge Problem: Velocity of propagation

- The velocities of propagation for the following waves:  $f = (0.05y-t)^2$ ,  $g = u(t+0.02x)$ ,  $h = \cos(2\pi 10^8 t - 2\pi z)$  are:

- $0.05\mathbf{a}_y, -0.02\mathbf{a}_x, 10^8 \mathbf{a}_z$
- $0.05\mathbf{a}_y, -0.02\mathbf{a}_x, -10^8 \mathbf{a}_z$
- $20\mathbf{a}_y, -50\mathbf{a}_x, 10^8 \mathbf{a}_z$
- $20\mathbf{a}_y, 50\mathbf{a}_x, 10^8 \mathbf{a}_z$
- $20\mathbf{a}_y, -50\mathbf{a}_x, -10^8 \mathbf{a}_z$

25

Goddard ECE329  
Lectures 18-20

From D3.11 (p 171) of old book

## Two useful identities

Forward wave  $\mathbf{a}_z$

$$E_x(z, t) \equiv f(t - \frac{z}{v_p}) \Rightarrow$$

$$E_x(z, t) = E_x(0, t - \frac{z}{v_p}) = E_x(z - v_p t, 0)$$

Backwards wave  $-\mathbf{a}_z$

$$E_x(z, t) \equiv g(t + \frac{z}{v_p}) \Rightarrow$$

$$E_x(z, t) = E_x(0, t + \frac{z}{v_p}) = E_x(z + v_p t, 0)$$

These identities simply say that the forward wave moves like  $z=v_p t$  and the backwards wave like  $z=-v_p t$


They allow you to express the wave solutions in terms of the wave at a fixed position or at a fixed time

26

Goddard ECE329  
Lectures 18-20

## Moving waveform

- A wave traveling in the  $-\mathbf{a}_z$  direction with speed 100 m/s is measured at  $z=0$ :



Find the wave amplitude at:

- $z=200\text{m}, t=0.2\text{s}$
- $z=-300\text{m}, t=3.4\text{s}$
- $z=100\text{m}, t=0.6\text{s}$

27

Goddard ECE329  
Lectures 18-20

From D3.13 (p 171) of old book

## Lecture 18 Summary

- Differentiate Maxwell's Equations

$$\vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t} \quad \vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$$

to derive wave equation:  $\frac{\partial^2 E_x}{\partial z^2} = \mu_0 \epsilon_0 \frac{\partial^2 E_x}{\partial t^2}$

which has solution:

$$E_x(z, t) = \underbrace{Af(t - \frac{z}{v_p})}_{\text{Traveling wave } +z \text{ direction}} + \underbrace{Bg(t + \frac{z}{v_p})}_{\text{Traveling wave } -z \text{ direction}}$$

Goddard ECE329  
Lectures 18-20

28

## Lecture 19 Sections 4.4, 4.5

### Uniform Plane Waves in Free Space

Adapted from Prof. Cunningham's Notes

29


Goddard ECE329  
Lectures 18-20

## Summary so far ...

- We have  $\mathbf{E}$  and  $\mathbf{H}$  that are
  - Perpendicular to each other
  - Perpendicular to the direction of propagation
  - Magnitude is constant ("uniform") in any plane perpendicular to the propagation direction

$$\begin{aligned}\vec{J}_s &= -J_x(t)\vec{a}_x \\ \vec{E} &= E_x(z, t)\vec{a}_x \\ \vec{H} &= H_y(z, t)\vec{a}_y\end{aligned}$$

Goddard ECE329  
Lectures 18-20



30

## Our solution so far ...

$$E_x(z,t) = Af(t - \frac{z}{v_p}) + Bg(t + \frac{z}{v_p})$$

$$H_y(z,t) = \frac{1}{\eta_0} \left[ Af(t - \frac{z}{v_p}) - Bg(t + \frac{z}{v_p}) \right]$$

Solution is a superposition of traveling waves


- one going in  $+z$  direction
- one going in  $-z$  direction

Goddard ECE329  
Lectures 18-20

31

For a valid solution, the waves move away from source

- Generated waves travel in the  $+z$  direction for  $z > 0$  and  $-z$  direction for  $z < 0$



$z \leq 0$  then  $A=0$

$$E_x(z,t) = Bg(t + \frac{z}{v_p})$$

$$H_y(z,t) = -\frac{B}{\eta_0} g(t + \frac{z}{v_p})$$

$$E_x(z,t) = Af(t - \frac{z}{v_p})$$


$$H_y(z,t) = \frac{A}{\eta_0} f(t - \frac{z}{v_p})$$

32

Goddard ECE329  
Lectures 18-20

## Final Step: Boundary conditions from the current source

We have to replace unknown functions  $f$  &  $g$  and constants  $A$  &  $B$  with something that relates them to the current source



Goddard ECE329  
Lectures 18-20

33

Near the boundary  $z \rightarrow 0$  from the  $z < 0$  and  $z > 0$  sides

$z=0^-$

$$E_x(z,t) = Bg(t)$$

$$H_y(z,t) = -\frac{B}{\eta_0} g(t)$$

$z=0^+$

$$E_x(z,t) = Af(t)$$

$$H_y(z,t) = \frac{A}{\eta_0} f(t)$$

34

Goddard ECE329  
Lectures 18-20


Apply Faraday's Law to closed path cutting through sheet that is parallel to current flow

$$\oint_C \vec{E} \cdot d\vec{l} = -\frac{d}{dt} \int_S \vec{B} \cdot d\vec{s}$$

$$\oint_C \vec{E} \cdot d\vec{l} = 0$$

$\vec{E}_t$  is continuous

$$E_{1t} = E_{2t}$$



35

Goddard ECE329  
Lectures 18-20

Use  $E_t$  continuous to match the solutions for  $z < 0$  and  $z > 0$


$\vec{E}_t$  is continuous

$$E_x(z=0^+) \Delta x - E_x(z=0^-) \Delta x = 0$$

$$Af(t) - Bg(t) = 0$$

$$Af(t) = Bg(t)$$

$$E_{1t} = E_{2t}$$



36

Goddard ECE329  
Lectures 18-20

## Eliminate $B_g$ in favor of $A_f$

$$\underline{z=0^-} \quad E_x(z, t) = A f(t)$$

$$H_y(z, t) = -\frac{A}{\eta_0} f(t)$$

$$\underline{z=0^+} \quad E_x(z, t) = A f(t)$$

$$H_y(z, t) = \frac{A}{\eta_0} f(t)$$

37

Goddard ECE329  
Lectures 18-20

Apply Ampere's Law to closed path cutting through sheet that is perpendicular to current

$$\oint_C \vec{H} \cdot d\vec{l} = I_{\text{enclosed}} + \frac{d}{dt} \iint_S \epsilon_0 \vec{E} \cdot d\vec{S}$$

$$\oint_C \vec{H} \cdot d\vec{l} = I_{\text{enclosed}}$$

$\vec{H}_t$  is discontinuous at current sheet

$$(\vec{H}_1 - \vec{H}_2)_y = \vec{J}_s \times \hat{a}_n$$

Goddard ECE329  
Lectures 18-20

$$\vec{J}_s = -J_s(t) \hat{a}_x$$

At  $z=0$

$J_s$  is a surface current in Amps per meter

38

Use  $H_{||}$  discontinuity to relate the solutions to the current sheet

$\vec{H}_t$  is discontinuous at sheet

$$H_y(z=0^+) \Delta y - H_y(z=0^-) \Delta y = J_s \Delta y$$

$$\frac{A}{\eta_0} f(t) + \frac{A}{\eta_0} f(t) = J_s(t)$$

$$\frac{2A}{\eta_0} f(t) = J_s(t)$$

$$Af(t) = \frac{\eta_0}{2} J_s(t)$$

$$\vec{J}_s = -J_s(t) \hat{a}_x$$

At  $z=0$

$J_s$  is a surface current in Amps per meter

39

Goddard ECE329  
Lectures 18-20

The final answer at last

$z < 0$

$$E_x(z, t) = \frac{\eta_0}{2} J_s(t + \frac{z}{v_p})$$

$$H_y(z, t) = -\frac{1}{2} J_s(t + \frac{z}{v_p})$$

$z > 0$

$$E_x(z, t) = \frac{\eta_0}{2} J_s(t - \frac{z}{v_p})$$

$$H_y(z, t) = \frac{1}{2} J_s(t - \frac{z}{v_p})$$


40

Goddard ECE329  
Lectures 18-20

Combining the expressions...

$$\vec{E}(z, t) = \frac{\eta_0}{2} J_s(t \mp \frac{z}{v_p}) \hat{a}_x$$

$$\vec{H}(z, t) = \pm \frac{1}{2} J_s(t \mp \frac{z}{v_p}) \hat{a}_y \quad z \gtrless 0$$




41

Goddard ECE329  
Lectures 18-20

Transforming time and space

- A wave travelling in the  $\hat{a}_z$  direction with speed 100m/s is measured at  $t=0$ :



Sketch:

- $E(z, 1s)$
- $E(0, t)$
- $E(200m, t)$

Goddard ECE329  
Lectures 18-20

From Problem 3.22 (p 200) of old book

42

## Lecture 19a Summary

- Wave emanates from  $z=0$  so must travel  $+a_z$  for  $z>0$  and  $-a_z$  for  $z<0$
- Use integral form of Maxwell's Eqns to get BOUNDARY CONDITIONS

$\vec{E}_t$  is continuous

$$E_x(0^+) = E_x(0^-)$$

$\vec{H}_t$  is discontinuous


$$H_y(0^+) - H_y(0^-) = J_s$$

Goddard ECE329  
Lectures 18-20

43

## Sinusoidal Plane Waves

- Infinite plane sheet of current at  $z=0$



Goddard ECE329  
Lectures 18-20

44

## Solution ...


$$\vec{J}_s = -J_{s0} \cos(\omega t) \vec{a}_x \quad \vec{E}(z,t) = \frac{\eta_0}{2} J_s(t \mp \frac{z}{v_p}) \vec{a}_x \quad \vec{H}(z,t) = \pm \frac{1}{2} J_s(t \mp \frac{z}{v_p}) \vec{a}_y$$

$$\begin{aligned} \vec{E}(z,t) &= \frac{\eta_0 J_{s0}}{2} \cos(\omega t \mp \beta z) \vec{a}_x & z \gtrless 0 \\ \vec{H}(z,t) &= \pm \frac{J_{s0}}{2} \cos(\omega t \mp \beta z) \vec{a}_y & \beta = \frac{\omega}{v_p} \end{aligned}$$

Goddard ECE329  
Lectures 18-20

45

## Web Demo



Goddard ECE329  
Lectures 18-20

46

## Wave Parameters

$$\vec{E}(z,t) = \frac{\eta_0 J_{s0}}{2} \cos(\omega t \mp \beta z) \vec{a}_x$$

|                   |  |               |
|-------------------|--|---------------|
| Phase             | $\phi = \omega t \mp \beta z$                  | (radians)     |
| Angular Frequency | $\omega = \frac{\partial \phi}{\partial t}$    | (radians/sec) |
| Linear Frequency  | $f = \frac{\omega}{2\pi}$                      | (1/sec)       |
| Phase Constant    | $\beta = \mp \frac{\partial \phi}{\partial z}$ | (radians/m)   |
| Wavelength        | $\lambda = \frac{2\pi}{\beta}$                 | (m)           |
| Phase Velocity    | $v_p = \frac{\omega}{\beta}$                   | (m/sec)       |

47

Goddard ECE329  
Lectures 18-20

## Sinusoidal wave parameters

For a wave in free space, find the following:

- $f$  if the phase of the field at a point changes  $3\pi$  in  $0.1\mu s$
- $\lambda$  if the phase changes  $0.04\pi$  in  $1m$
- $f$  if  $\lambda=25m$
- $\lambda$  if  $f=5MHz$

Goddard ECE329  
Lectures 18-20

From D3.14 (p 178) of old book

48

## A few additional important properties

$$v_p = \lambda f$$

Speed of light in free space

$$\frac{|\vec{E}|}{|\vec{H}|} = \eta_0$$


Intrinsic impedance of free space

Goddard ECE329  
Lectures 18-20

49

## Poynting Vector

- “Points” in the direction of energy flow
- Energy flux density



Power per unit area

$$\vec{S} = \vec{E} \times \vec{H} = \pm \frac{\eta_0 J_{S0}^2}{4} \cos^2(\omega t \mp \beta z) \hat{a}_z \quad z \geq 0$$

Goddard ECE329  
Lectures 18-20


50

## Notice the Triad (permutations)

$$\hat{S} = \hat{E} \times \hat{H}$$

$$\hat{E} = \hat{H} \times \hat{S}$$

$$\hat{H} = \hat{S} \times \hat{E}$$



$$\hat{a}_z = \hat{a}_x \times \hat{a}_y$$

$$\hat{a}_x = \hat{a}_y \times \hat{a}_z$$

$$\hat{a}_y = \hat{a}_z \times \hat{a}_x$$



Similar to coordinate axes



51

Goddard ECE329  
Lectures 18-20

## Challenge problem: Finding field directions

- If  $\mathbf{H} = H_0 \cos(6\pi \times 10^8 t + 2\pi y) \mathbf{a}_x$  A/m, then the directions of: (1)  $\mathbf{H}$  at  $t=0$ ,  $y=0$ , (2) propagation, and (3)  $\mathbf{E}$  at  $t=0$ ,  $y=0$  are:

- $\mathbf{a}_x, -\mathbf{a}_y, -\mathbf{a}_x$
- $\mathbf{a}_x, \mathbf{a}_y, \mathbf{a}_z$
- $\mathbf{a}_x, \mathbf{a}_y, -\mathbf{a}_x$
- $\mathbf{a}_x, -\mathbf{a}_y, -\mathbf{a}_z$
- $\mathbf{a}_x, \mathbf{a}_y, -\mathbf{a}_z$

Goddard ECE329  
Lectures 18-20

From D3.15 (p 178) of old book

52

## Example: Antenna Array

- An antenna array consists of two or more antenna elements spaced appropriately and excited with currents of appropriate amplitude and phase. Find  $\mathbf{E}$  everywhere if:

$$\mathbf{J}_{s1} = -J_{s0} \cos \omega t \mathbf{a}_x \text{ at } z=0$$

$$\mathbf{J}_{s2} = -J_{s0} \sin \omega t \mathbf{a}_x \text{ at } z=\lambda/4$$

Goddard ECE329  
Lectures 18-20

From Example 3.12 (p 177) of old book

53

## Lecture 19 Summary

- Sinusoidal waves

$$\phi = \omega t \mp \beta z \quad \omega = \frac{\partial \phi}{\partial t} \quad f = \frac{\omega}{2\pi}$$

$$\beta = \mp \frac{\partial \phi}{\partial z} \quad \lambda = \frac{2\pi}{\beta} \quad v_p = \frac{\omega}{\beta}$$

$$v_p = \lambda f \quad \left| \frac{E}{H} \right| = \eta_0$$

- Poynting vector (power per unit area) is in direction of energy flow

$$\vec{S} = \vec{E} \times \vec{H}$$

- $\mathbf{E}$ ,  $\mathbf{H}$ ,  $\mathbf{S}$  form a triad

Goddard ECE329  
Lectures 18-20

54

## Lecture 20 Section 4.6

### Power Flow/Energy Storage Poynting's Theorem


Adapted from Prof. Cunningham's Notes

55

Goddard ECE329  
Lectures 18-20

## Field Source

- Infinite plane sheet of current at  $z=0$




56

Goddard ECE329  
Lectures 18-20

## Combining the expressions...

$$\vec{E}(z, t) = \frac{\eta_0}{2} J_s(t \mp \frac{z}{v_p}) \vec{a}_x \quad z \geq 0$$

$$\vec{H}(z, t) = \pm \frac{1}{2} J_s(t \mp \frac{z}{v_p}) \vec{a}_y$$



Goddard ECE329  
Lectures 18-20

57

## Definition: Poynting Vector

The POWER provided by the current source is used to generate the propagating  $\mathbf{E}$  and  $\mathbf{H}$  fields.

The  $\mathbf{E}$  and  $\mathbf{H}$  fields are carrying power with them as they propagate

$$\vec{S} = \vec{E} \times \vec{H}$$

Definition for the Power Flow Density of an EM Field

Units for  $\mathbf{S}$ : Watts/m<sup>2</sup>

58

Goddard ECE329  
Lectures 18-20

## Integral & Differential Forms

$$\vec{S} = \vec{E} \times \vec{H}$$

"Instantaneous" Poynting vector

We can calculate power density magnitude and direction for any single place and time if we know  $\mathbf{E}$  and  $\mathbf{H}$  at that place and time.

$$\oint_S \vec{S} \bullet d\vec{S} = \iint_S (\vec{E} \times \vec{H}) \bullet d\vec{S}$$


Power flow out of a CLOSED surface (units = Watts)

59

Goddard ECE329  
Lectures 18-20

## There's ENERGY in the field!

If the EM field is carrying POWER, how much ENERGY is contained in any given VOLUME of space?



60


Goddard ECE329  
Lectures 18-20

## How much ENERGY?

$$\vec{S} = \vec{E} \times \vec{H} = |E_x| |H_y| \hat{a}_z$$

Use integral form to get a special case of Poynting's Theorem and calculate the power flow OUT of our little closed volume

$$\iint_S \vec{S} \cdot d\vec{S} =$$



How much energy is "stored" in **E** and **H** for this volume  $dV$ ?

$$\iint_S \vec{S} \cdot d\vec{S} = \frac{\partial [E_x H_y]}{\partial z} \Delta V =$$

Hint: Use slide 14 result:

$$\frac{\partial E_x}{\partial z} = -\frac{\partial B_y}{\partial z} = -\mu_0 \frac{\partial H_y}{\partial z}$$

$$\frac{\partial H_z}{\partial z} = -J_x - \frac{\partial D_z}{\partial z} = -J_x - \epsilon_0 \frac{\partial E_z}{\partial z}$$

61

Goddard ECE329  
Lectures 18-20

## A question we may ask on an exam

The power is not a constant value as a function of time.  
Remember - it has that  $\cos^2(t)$  dependence.

What is the TIME-AVERAGED power being carried by the EM field?

Do derivation - it contains a trig identity

62

Goddard ECE329  
Lectures 18-20

## Power calculations

- For  $\mathbf{H}=H_0 \cos(6\pi \times 10^7 t - 0.2\pi z) \mathbf{a}_y$  A/m, find:
  - the instantaneous power flow across a  $1 \text{ m}^2$  area,  $A$ , in the  $z=0$  plane at  $t=0$
  - the instantaneous power across  $A$  at  $t=1/8\mu\text{s}$
  - the time averaged power flow across  $A$

63

Goddard ECE329  
Lectures 18-20

From D3.19 (p 191) of old book

## Challenge Question: Power flow

- For  $\mathbf{H}=H_0 \cos(6\pi \times 10^7 t - 0.2\pi z) \mathbf{a}_y$  A/m, and  $A_{@z_0}$  is a  $1\text{m}^2$  area at the plane  $z=z_0$  which statement is true:

- the instantaneous power flow crossing  $A_{@1\text{m}}$  in the  $\mathbf{a}_z$  direction can be negative
- the time averaged power flow across  $A_{@1\text{m}}$  in the  $\mathbf{a}_z$  direction can be negative
- the instantaneous power flow across  $A_{@z_0}$  at  $t=0$  depends on the position  $z_0$
- the time averaged power flow across  $A_{@z_0}$  at  $t=0$  depends on the position  $z_0$

64

Goddard ECE329  
Lectures 18-20

LG's question

## Poynting's Theorem

Begin with:  $\nabla \bullet \vec{S} = \nabla \bullet (\vec{E} \times \vec{H}) = \vec{H} \bullet (\nabla \times \vec{E}) - \vec{E} \bullet (\nabla \times \vec{H})$

65

Goddard ECE329  
Lectures 18-20

## Poynting's Theorem

$$\text{Thus, } \nabla \bullet \vec{S} = -\frac{\partial}{\partial t} \left( \frac{1}{2} \epsilon_0 E^2 \right) - \frac{\partial}{\partial t} \left( \frac{1}{2} \mu_0 H^2 \right) - \vec{E} \bullet \vec{J}$$

$$\nabla \bullet \vec{S} + \vec{E} \bullet \vec{J} = -\frac{\partial u_e}{\partial t} - \frac{\partial u_m}{\partial t}$$

$$-\frac{\partial}{\partial t} (u_e + u_m) = \nabla \bullet \vec{S} + \vec{E} \bullet \vec{J}$$

$$u_e = \frac{1}{2} \epsilon_0 E^2, \quad u_m = \frac{1}{2} \mu_0 H^2$$

$u_e$ =electric field energy density

$u_m$ =magnetic field energy density

66

Goddard ECE329  
Lectures 18-20

## Poynting's Theorem

$$-\frac{\partial}{\partial t}(u_m + u_e) = \nabla \cdot \vec{S} + \vec{E} \cdot \vec{J}$$

Integrate over the volume and Apply Divergence Theorem:

$$-\frac{\partial}{\partial t} \iiint_V (u_m + u_e) dV = \iint_S \vec{S} \cdot d\vec{S} + \iiint_V \vec{E} \cdot \vec{J} dV$$

Rate the fields **LOSE** energy = Power flow **OUT** of surface + Rate of work done **BY** the fields

Can be + or -      Can be + or -       $\vec{E} \cdot \vec{J}$  is non-negative:  
 $J = \sigma E$  so  $\vec{E} \cdot \vec{J} = \sigma |\vec{E}|^2 \geq 0$   
Zero only when  $\sigma=0$ , i.e.  
in a perfect dielectric


67

Goddard ECE329  
Lectures 18-20

## Poynting's Theorem for Perfect Dielectric

$$\vec{J} = \sigma \vec{E} = 0 \Rightarrow \iint_S \vec{S} \cdot d\vec{S} = -\frac{\partial}{\partial t} \iiint_V (u_m + u_e) dV$$

If net power flows out, the energy stored inside must decrease



$$P_{out}^{net} > 0$$

$$\text{Energy stored} = \iiint_V (u_m + u_e) dV \text{ is decreasing}$$

69

Goddard ECE329  
Lectures 18-20

## Time Averaged Poynting Vector

$$\vec{E} = \operatorname{Re}[\vec{E} e^{j\omega t}] = \frac{\vec{E} e^{j\omega t} + \vec{E}^* e^{-j\omega t}}{2}$$

$$\langle \vec{S} \rangle = \langle \vec{E} \times \vec{H} \rangle = \left\langle \frac{\vec{E} e^{j\omega t} + \vec{E}^* e^{-j\omega t}}{2} \times \frac{\vec{H} e^{j\omega t} + \vec{H}^* e^{-j\omega t}}{2} \right\rangle$$

$$= \frac{1}{4} \left\langle \vec{E} \times \vec{H} e^{2j\omega t} + \vec{E} \times \vec{H}^* + \vec{E}^* \times \vec{H} + \vec{E}^* \times \vec{H}^* e^{-2j\omega t} \right\rangle$$

$$\langle \vec{S} \rangle = \frac{1}{2} \operatorname{Re}[\vec{E} \times \vec{H}^*] = \frac{1}{2} \operatorname{Re}[(\bar{\eta} \vec{H}) \vec{H}^*] \hat{s} = \frac{1}{2} |\vec{H}|^2 \operatorname{Re}[\bar{\eta}] \hat{s}$$

" $\tilde{E} = \bar{\eta} \tilde{H}$ " but  $\tilde{E}, \tilde{H}$  point in different directions

71

Goddard ECE329  
Lectures 18-20

## Rate of work done by the fields

$$dq = \rho dV \quad d\vec{l} = \vec{v} dt \quad \vec{E} \rightarrow \int_S \vec{S} \cdot d\vec{S} = \iint_V \nabla \cdot \vec{S} dV$$

Work done moving dq a distance  $d\vec{l}$  is  $dW = \vec{F} \cdot d\vec{l}$

$$d\vec{F} = dq \vec{E}$$

Rate of work done **BY** the fields moving a small charge dq:

$$\frac{dW}{dt} = d\vec{F} \cdot \frac{d\vec{l}}{dt} = d\vec{F} \cdot \vec{v} = dq \vec{E} \cdot \vec{v} = \vec{E} \cdot (\rho \vec{v}) dV = (\vec{E} \cdot \vec{J}) dV$$

$$\therefore \iiint_V \vec{E} \cdot \vec{J} dV = \text{Rate of work done by the fields (Joule heating)}$$

68

Goddard ECE329  
Lectures 18-20

## Challenge Question: Poynting's Theorem

- If  $\mathbf{H} = H_0 \cos(\omega t + x) \mathbf{a}_y$  A/m and  $\mathbf{E} = \eta_0 H_0 \cos(\omega t + x) \mathbf{a}_z$  V/m in the *free space* region  $x > 0$ , which statement is **true** for  $V$ , the volume bounded by the  $x=0$  and  $x=1$  planes
  - the net outward power flow is zero at all times
  - the fields do work and thus lose energy
  - the total electric field energy inside is constant in time
  - the time averaged electric field energy density at each position  $x$  is constant in time
  - the total electric and magnetic field energy density at fixed position  $x$  is constant in time

Goddard ECE329  
Lectures 18-20

LG's question

## Lecture 20 Summary

### Poynting's Theorem:

- Rate that stored field energy is lost = rate that energy flows out boundary surface + rate that the fields do work (Joule heating)

$$-\frac{\partial}{\partial t} \iiint_V (w_e + w_m) dV = \iint_S \vec{S} \cdot d\vec{S} + \iiint_V \vec{E} \cdot \vec{J} dV$$

- Time averaged Poynting vector

$$\langle \vec{S} \rangle = \frac{1}{2} \operatorname{Re}[\vec{E} \times \vec{H}^*]$$

### Next up: Waves in materials

- Sections 5.3-5.4

72

Goddard ECE329  
Lectures 18-20

## Lectures 21-24 Sections 5.3-5.4

### Plane Waves in Materials

Also Section 1.4: Polarization

Adapted from Prof. Cunningham's Notes


1

Goddard ECE329  
Lectures 21-24

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited


### 3 types of materials

#### Conductors




**Free electrons**

#### Dielectrics



**Polarized atoms/molecules**  
**Bound electrons**

#### Magnetic



**Magnetic moments**  
**Bound electrons**

$\mathbf{E} = 0$  inside  
 $\rho = 0$  inside  
 $\rho = \rho_s$  only surface charge  
 $V$  is same throughout  
 $\mathbf{E}_{\text{outside}}$  is  $\perp$  to surface

Goddard ECE329  
Lectures 21-24

$\mathbf{E} \neq 0$  inside but it is reduced  
 $\mathbf{E}_{\text{tot}} = \mathbf{E}_a + \mathbf{E}_s$   
 $\mathbf{D} = \epsilon \mathbf{E}_{\text{tot}} = \mathbf{P} + \epsilon_0 \mathbf{E}_{\text{tot}}$

$\mathbf{B}_{\text{tot}} = \mathbf{B}_s + \mathbf{B}_a$   
 $\mathbf{B}_{\text{tot}} = \mu \mathbf{H} = \mu_0 (\mathbf{H} + \mathbf{M})$

2

### New Relations

$$\vec{J} = \sigma \vec{E}$$

$$\vec{D} = \epsilon \vec{E} \quad \epsilon = \epsilon_0 \epsilon_r$$

$$\vec{B} = \mu \vec{H} \quad \mu = \mu_0 \mu_r$$

3

Goddard ECE329  
Lectures 21-24

### Inside a material, Maxwell's Equations become:

#### Free Space

$$\vec{\nabla} \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$$

$$\vec{\nabla} \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

$$\vec{\nabla} \bullet \vec{D} = \rho$$

$$\vec{\nabla} \bullet \vec{B} = 0$$

#### Inside Material

$$\vec{\nabla} \times \vec{H} = \sigma \vec{E} + \epsilon \frac{\partial \vec{E}}{\partial t}$$

$$\vec{\nabla} \times \vec{E} = -\mu \frac{\partial \vec{H}}{\partial t}$$

$$\vec{\nabla} \bullet (\epsilon \vec{E}) = \rho$$

$$\vec{\nabla} \bullet \vec{H} = 0$$

4

Goddard ECE329  
Lectures 21-24

A single material can have conductive, dielectric, and magnetic properties AT THE SAME TIME

$$\sigma \neq 0$$

$$\epsilon_r \neq 1$$

$$\mu_r \neq 1$$


How does an EM wave propagate through this?

5

Goddard ECE329  
Lectures 21-24

### Field Source

- Infinite plane sheet of current at  $z=0$



6

## Solution

$$\vec{E}(z,t) = \frac{\eta_0 J_{s0}}{2} \cos(\omega t \mp \beta z) \vec{a}_x$$

$$\vec{H}(z,t) = \pm \frac{J_{s0}}{2} \cos(\omega t \mp \beta z) \vec{a}_y$$


$$\beta = \frac{\omega}{v_p}$$

z ≥ 0

7

Goddard ECE329  
Lectures 21-24

## Web Demo



<http://www.phy.ntnu.edu.tw/java/emWave/emWave.html>

Goddard ECE329  
Lectures 21-24

## Key characteristics in FREE SPACE

- No attenuation
- $E_x$  and  $H_y$  are IN PHASE for linear polarization
- Impedance:  $|\vec{E}| = \eta_0 |\vec{H}|$
- Travel at Speed of Light:  $v_p = c = \omega/\beta$
- Perpendicular:  $\mathbf{E} \perp \mathbf{H} \perp \mathbf{S}$


$$\vec{S} = \vec{E} \times \vec{H}$$

9

Goddard ECE329  
Lectures 21-24

## Field Source in a MATERIAL

- Infinite plane sheet of current at  $z=0$



10

Goddard ECE329  
Lectures 21-24

## Similar Procedure for Maxwell's Equations

- We will SIMULTANEOUSLY solve Maxwell's equations to find  $\mathbf{E}$  and  $\mathbf{H}$  caused by  $\mathbf{J}$ 
  - Note:  $\mathbf{J} = \sigma \mathbf{E} \neq 0$  inside the material

$$\vec{\nabla} \times \vec{E} = -\mu \frac{\partial \vec{H}}{\partial z} \quad \vec{E} = E_x(z,t) \vec{a}_x$$

$$\vec{\nabla} \times \vec{H} = \sigma \vec{E} + \epsilon \frac{\partial \vec{E}}{\partial z} \quad \vec{H} = H_y(z,t) \vec{a}_y$$

$$\vec{J}_s = -J_x(t) \vec{a}_x$$

11

Goddard ECE329  
Lectures 21-24

## Apply the two Maxwell's Equations

- Performing the cross product, only two equations contain  $E_x$  or  $H_y$

$$\frac{\partial E_x}{\partial z} = -\mu \frac{\partial H_y}{\partial t}$$

$$\frac{\partial H_y}{\partial z} = -\sigma E_x - \epsilon \frac{\partial E_x}{\partial t}$$

The key difference

12

Goddard ECE329  
Lectures 21-24

Reminder from Lecture 11

## Phasor Review


$$e^{j\theta} = \cos \theta + j \sin \theta$$

$$\cos(\theta) = \operatorname{Re}[e^{j\theta}]$$

$$\sin(\theta) = \operatorname{Re}[-je^{j\theta}] = \operatorname{Re}[e^{j(\theta-\pi/2)}]$$

$$\operatorname{Re}[z] = (z + z^*)/2$$

$$\begin{aligned} E_x(z, t) &= E_x(z) \cos(\omega t \mp \beta z + \theta) \\ &= \operatorname{Re}[E_x(z) e^{\mp j\beta z} e^{j\theta} e^{j\omega t}] \\ &= \operatorname{Re}[\tilde{E}_x(z) e^{j\omega t}] \end{aligned}$$



13

Goddard ECE329  
Lectures 21-24

## Solve PDEs with Phasors

- Technique simplifies the algebra

$$E_x(z, t) = \operatorname{Re}[\tilde{E}_x(z) e^{j\omega t}] \quad H_y(z, t) = \operatorname{Re}[\tilde{H}_y(z) e^{j\omega t}]$$

$$\frac{\partial E_x}{\partial t} = \operatorname{Re}[j\omega \tilde{E}_x(z) e^{j\omega t}] \quad \boxed{\frac{\partial}{\partial t} \equiv j\omega}$$

$$\frac{\partial E_x}{\partial z} = -\mu \frac{\partial H_y}{\partial t}$$

$$\frac{\partial H_y}{\partial z} = -\sigma \tilde{E}_x - \varepsilon \frac{\partial E_x}{\partial t}$$

$$\boxed{\frac{\partial \tilde{E}_x}{\partial z} = -\mu(j\omega) \tilde{H}_y} \quad \boxed{\frac{\partial \tilde{H}_y}{\partial z} = -\sigma \tilde{E}_x - \varepsilon(j\omega) \tilde{E}_x}$$

Goddard ECE329  
Lectures 21-24

14

## Differentiate again in z

$$\begin{aligned} \frac{\partial \tilde{E}_x}{\partial z} &= -\mu(j\omega) \tilde{H}_y \\ \frac{\partial \tilde{H}_y}{\partial z} &= -\sigma \tilde{E}_x - \varepsilon(j\omega) \tilde{E}_x \end{aligned} \quad \left. \begin{aligned} \frac{\partial^2 \tilde{E}_x}{\partial z^2} &= -\mu(j\omega) \frac{\partial \tilde{H}_y}{\partial z} \\ &= -\mu(j\omega) [-\sigma \tilde{E}_x - \varepsilon(j\omega) \tilde{E}_x] \\ &= j\omega \mu (\sigma + j\omega \varepsilon) \tilde{E}_x \end{aligned} \right.$$

$$\boxed{\frac{\partial^2 \tilde{E}_x}{\partial z^2} = \bar{\gamma}^2 \tilde{E}_x}$$

$$\bar{\gamma} \equiv \sqrt{j\omega \mu (\sigma + j\omega \varepsilon)} = \alpha + j\beta$$

15

Goddard ECE329  
Lectures 21-24

## Solve simple PDE and rewrite Phasors as Cosines

$$\frac{\partial^2 \tilde{E}_x}{\partial z^2} = \bar{\gamma}^2 \tilde{E}_x \quad \boxed{\tilde{E}_x(z) = \bar{A} e^{-\bar{\gamma}z} + \bar{B} e^{+\bar{\gamma}z}} \quad \bar{\gamma} = \alpha + j\beta$$

$$\begin{aligned} \tilde{E}_x(z) &= \bar{A} e^{-\alpha z} e^{-j\beta z} + \bar{B} e^{\alpha z} e^{j\beta z} \\ &= A e^{j\theta} e^{-\alpha z} e^{-j\beta z} + B e^{j\phi} e^{\alpha z} e^{j\beta z} \end{aligned}$$

$$\vec{E}_x(z, t) = \operatorname{Re}[\tilde{E}_x(z) e^{j\omega t}]$$

$$\boxed{\vec{E}_x(z, t) = A e^{-\alpha z} \cos(\omega t - \beta z + \theta) + B e^{\alpha z} \cos(\omega t + \beta z + \phi)}$$

$z > 0$

$z < 0$

16

Goddard ECE329  
Lectures 21-24

## Also Solve for $H_y$

$$\boxed{\vec{E}_x(z, t) = A e^{-\alpha z} \cos(\omega t - \beta z + \theta) + B e^{\alpha z} \cos(\omega t + \beta z + \phi)}$$

$\underbrace{\qquad}_{z>0} \qquad \underbrace{\qquad}_{z<0}$

$$\frac{\partial \tilde{E}_x}{\partial z} = -\mu(j\omega) \tilde{H}_y \quad \bar{\eta} \equiv \sqrt{\frac{j\omega \mu}{\sigma + j\omega \varepsilon}} = |\bar{\eta}| e^{j\tau}$$

$$\boxed{\vec{H}_y(z, t) = \frac{A}{|\bar{\eta}|} e^{-\alpha z} \cos(\omega t - \beta z + \theta - \tau) - \frac{B}{|\bar{\eta}|} e^{\alpha z} \cos(\omega t + \beta z + \phi - \tau)}$$

$\underbrace{\qquad}_{z>0} \qquad \underbrace{\qquad}_{z<0}$

17

Goddard ECE329  
Lectures 21-24


Apply Faraday's Law to closed path cutting through sheet that is parallel to current flow

$$\oint_C \vec{E} \bullet d\vec{l} = -\frac{d}{dt} \int_S \vec{B} \bullet d\vec{S}$$

$$\oint_C \vec{E} \bullet d\vec{l} = 0$$

$\vec{E}_{||}$  is continuous

$$\begin{aligned} E_x(z=0^+) \Delta x - E_x(z=0^-) \Delta x &= 0 \\ A \cos(\omega t + \theta) - B \cos(\omega t + \phi) &= 0 \\ \therefore A = B \text{ and } \theta = \phi \end{aligned}$$



18

Goddard ECE329  
Lectures 21-24

Apply Ampere's Law to closed path cutting through sheet that is perpendicular to current

$$\oint_C \vec{H} \cdot d\vec{l} = I_{\text{enclosed}} + \frac{d}{dt} \iint_S \epsilon_0 \vec{E} \cdot d\vec{S}$$

$$\oint_C \vec{H} \cdot d\vec{l} = I_{\text{enclosed}}$$

$\vec{H}_{||}$  is discontinuous at sheet

$$H_y(z=0^+) \Delta y - H_y(z=0^-) \Delta y = J_s \Delta y$$

$$\frac{2A}{|\bar{\eta}|} \cos(\omega t + \theta - \tau) = J_{s0} \cos(\omega t)$$

$$\therefore A = \frac{|\bar{\eta}| J_{s0}}{2} \text{ and } \theta = \tau$$

Goddard ECE329  
Lectures 21-24

$$\vec{J}_s = -J_s(t) \hat{a}_x$$

At  $z=0$

$J_s$  is a surface current in Amps per meter

19

Final Solution for  $E_x$  and  $H_y$

$$\vec{E}(z,t) = \frac{|\bar{\eta}| J_{s0}}{2} e^{\mp \alpha z} \cos(\omega t \mp \beta z + \tau) \hat{a}_x$$

$$\vec{H}(z,t) = \frac{\pm J_{s0}}{2} e^{\mp \alpha z} \cos(\omega t \mp \beta z) \hat{a}_y \quad z \geq 0$$

Strength of fields drops exponentially according to the attenuation constant

Magnitude of  $E$  and  $H$  related through magnitude of the complex impedance,  $\bar{\eta}$

$E$  and  $H$  are out of phase by the phase of the complex impedance,  $\tau = \arg(\bar{\eta})$

20

## Phasor Solution for $E_x$ and $H_y$

$$J_x(z=0,t) = \operatorname{Re}[-\tilde{J}_{s0} e^{j\omega t}]$$

$$E_x(z,t) = \operatorname{Re}[\tilde{E}_x(z) e^{j\omega t}]$$

$$H_y(z,t) = \operatorname{Re}[\tilde{H}_y(z) e^{j\omega t}]$$

$$\tilde{E}_x(z) = \frac{\bar{\eta} \tilde{J}_{s0}}{2} e^{\mp \bar{\eta} z} \hat{a}_x$$

$$\tilde{H}_y(z) = \frac{\pm \tilde{J}_{s0}}{2} e^{\mp \bar{\eta} z} \hat{a}_y \quad z \geq 0$$

$\tilde{H}$  is in phase with the current source

$$\tilde{E}_x = \bar{\eta} \tilde{H}_y$$

holds for amplitude and for phase but they point in different directions

21

Goddard ECE329  
Lectures 21-24

## What is the same?

- Frequency of the wave =  $\omega$
- Perpendicular:  $\mathbf{E} \perp \mathbf{H} \perp \mathbf{S}$

$$\vec{S} = \vec{E} \times \vec{H}$$

23


Goddard ECE329  
Lectures 21-24

## What is different?

1. The magnitude of the wave is ATTENUATED

Gets weaker by  $e^{-\alpha z}$  for a wave travelling in  $+z$

$\alpha$  = "Attenuation Constant"  
Units = 1/m or Np/m or dB/m



24

Goddard ECE329  
Lectures 21-24

## What is different?

2. Magnitude relationship between E and H

$$|\vec{E}| = |\bar{\eta}| |\vec{H}|$$

$$\bar{\eta} \neq \eta_0$$

$\bar{\eta}$  = "Complex Impedance" of the material (because it is a complex number)

$|\bar{\eta}|$  = Magnitude of the complex impedance (Units = Ohms)


Goddard ECE329  
Lectures 21-24

25

## What is different?

3. **E** and **H** are OUT OF PHASE by  $\tau$

$\tau$  = "Phase Offset"  
Units = radians



Goddard ECE329  
Lectures 21-24

26

## What is different?

4. Speed of propagation is no longer c in free space

$$v_p = \frac{\omega}{\beta}$$

Is still good

But  $\beta$  will be related to properties of the material and actually,  $\beta$  can depend on  $\omega$

If relation  $\beta(\omega)$  is nonlinear, then the material has dispersion (different frequencies travel at different speeds, e.g. colors separate in a prism due to this dispersion) and thus a pulse (Fourier series - sum of waves) can change its shape as the pulse propagates

27

Goddard ECE329  
Lectures 21-24

## Challenge Question: Propagation in $\sigma=0$ medium

- Given the phasors:  $\tilde{E}_x(z) = \frac{\bar{\eta} \tilde{J}_{s0}}{2} e^{\pm j\tilde{\gamma} z} \hat{a}_x$     $\tilde{H}_y(z) = \frac{\pm \tilde{J}_{s0}}{2} e^{\mp j\tilde{\gamma} z} \hat{a}_y$

and definitions:  $\bar{\eta} \equiv \sqrt{\frac{j\omega\mu}{\sigma + j\omega\epsilon}} = |\bar{\eta}| e^{j\tau}$     $\tilde{\gamma} \equiv \sqrt{j\omega\mu(\sigma + j\omega\epsilon)} = \alpha + j\beta$   
If  $\sigma=0$  and  $\epsilon=2\epsilon_0$ , consider the veracity of the statements:

- The fields will attenuate as they propagate
- E** and **H** will be out of phase
- The velocity of propagation will be c

- (a) I only, (b) II only, (c) III only, (d) I, II, and III, (e) none are true

Goddard ECE329  
Lectures 21-24

LG's question

28

## Lecture 21-22a Summary

- Differentiate Maxwell's Equations

$$\vec{\nabla} \times \vec{E} = -\mu \frac{\partial \vec{H}}{\partial t} \quad \vec{\nabla} \times \vec{H} = \sigma \vec{E} + \epsilon \frac{\partial \vec{E}}{\partial t}$$

to get complex wave equation:  $\frac{\partial^2 \tilde{E}_x}{\partial z^2} = \tilde{\gamma}^2 \tilde{E}_x$   
which has decaying solutions:

$$\tilde{E}(z,t) = \frac{|\bar{\eta}| J_{s0}}{2} e^{\mp j\alpha z} \cos(\omega t \mp \beta z + \tau) \hat{a}_x \quad \tilde{E}_x(z) = \frac{\bar{\eta} \tilde{J}_{s0}}{2} e^{\mp j\tilde{\gamma} z} \hat{a}_x$$

$$\tilde{H}(z,t) = \frac{\pm J_{s0}}{2} e^{\mp j\alpha z} \cos(\omega t \mp \beta z) \hat{a}_y \quad \tilde{H}_y(z) = \frac{\pm \tilde{J}_{s0}}{2} e^{\mp j\tilde{\gamma} z} \hat{a}_y$$

29

Goddard ECE329  
Lectures 21-24

## ECE 329 Lectures 22b-23

### Plane Waves in Materials

Adapted from Prof. Cunningham's Notes

Goddard ECE329  
Lectures 21-24

30

## Hmm, Almost the entire Greek Alphabet!!!

$$\begin{array}{ll} \sigma & \alpha \\ \epsilon & \beta \\ \mu & \gamma \\ & \tau \\ & \eta \end{array}$$

These constants are material properties and affect wave propagation:  $\alpha, \beta, \gamma, \tau, \eta$

Goddard ECE329  
Lectures 21-24

31

## Wave Equation for $E_x$

$$\frac{\partial^2 \tilde{E}_x}{\partial z^2} = j\omega\mu(\sigma + j\omega\epsilon)\tilde{E}_x$$

(Propagation Constant)<sup>2</sup>  
Most important definition from last class

$$\frac{\partial^2 \tilde{E}_x}{\partial z^2} = \bar{\gamma}^2 \tilde{E}_x$$

$$\text{For wave in free space, wave eqn was: } \frac{\partial^2 E_x}{\partial z^2} = \mu_0 \epsilon_0 \frac{\partial^2 E_x}{\partial z^2}$$

Goddard ECE329  
Lectures 21-24

## Propagation Constant

$$\frac{\partial^2 \tilde{E}_x}{\partial z^2} = \bar{\gamma}^2 \tilde{E}_x$$

$$\bar{\gamma} = \sqrt{j\omega\mu(\sigma + j\omega\epsilon)} = \alpha + j\beta = |\gamma| e^{j\psi}$$

It's a COMPLEX NUMBER  $\bar{\gamma}^2$   
REAL PART + IMAGINARY PART

$$\text{Re}[\bar{\gamma}^2] < 0, \text{Im}[\bar{\gamma}^2] > 0 \Rightarrow 45^\circ \leq \psi \leq 90^\circ$$

$\therefore \bar{\gamma}^2$  is in Quadrant II  $\therefore \beta \geq \alpha \geq 0$

Goddard ECE329  
Lectures 21-24

33

## Propagation Constant

$$\bar{\gamma} = \alpha + j\beta = \sqrt{j\omega\mu(\sigma + j\omega\epsilon)}$$

Calculating  $\bar{\gamma}^2$  gives 2 equations and 2 unknowns  $\alpha, \beta$

$$\begin{aligned} \bar{\gamma}^2 &= \alpha^2 - \beta^2 + 2j\alpha\beta = -\omega^2\mu\epsilon + j\omega\mu\sigma \\ \therefore \alpha^2 - \beta^2 &= -\omega^2\mu\epsilon \quad \text{and} \quad 2\alpha\beta = \omega\mu\sigma \end{aligned}$$

Solving for  $\alpha$  and  $\beta$  using Mathematica:

$$\alpha = \omega \sqrt{\frac{\mu\epsilon}{2} \left( \sqrt{1 + \left( \frac{\sigma}{\omega\epsilon} \right)^2} - 1 \right)^{1/2}}$$

Attenuation Constant

$$\beta = \omega \sqrt{\frac{\mu\epsilon}{2} \left( \sqrt{1 + \left( \frac{\sigma}{\omega\epsilon} \right)^2} + 1 \right)^{1/2}}$$

Phase Constant

34

## The key relationships

$$\alpha = \omega \sqrt{\frac{\mu\epsilon}{2} \left( \sqrt{1 + \left( \frac{\sigma}{\omega\epsilon} \right)^2} - 1 \right)^{1/2}}$$

attenuation

$$e^{-\alpha z}$$

$$\beta = \omega \sqrt{\frac{\mu\epsilon}{2} \left( \sqrt{1 + \left( \frac{\sigma}{\omega\epsilon} \right)^2} + 1 \right)^{1/2}}$$

velocity

$$v_p = \omega / \beta$$

ATTENUATION AND VELOCITY ARE A FUNCTION OF  $\omega$

35

Goddard ECE329  
Lectures 21-24

## Complex Material Impedance

$$\bar{\eta} = \sqrt{\frac{j\omega\mu}{\sigma + j\omega\epsilon}}$$

$$\bar{\eta} = |\bar{\eta}| e^{j\tau}$$

Magnitude of Complex Impedance

Phase difference between  $E_x$  and  $H_y$

36

Goddard ECE329  
Lectures 21-24

## Solving for $|\eta|$ and $\tau$

$$\frac{\partial^2 \tilde{E}_x}{\partial z^2} = \bar{\gamma}^2 \tilde{E}_x$$

$$\tilde{E}_x(z) = \begin{cases} \bar{A}e^{-\bar{\gamma}z} & z > 0 \\ \bar{B}e^{+\bar{\gamma}z} & z < 0 \end{cases}$$

$$\frac{\partial \tilde{E}_x}{\partial z} = -\mu(j\omega)\tilde{H}_y$$

$$\tilde{H}_y(z) = \begin{cases} -\bar{\gamma}\bar{A}e^{-\bar{\gamma}z} = \frac{j\bar{\gamma}\tilde{E}}{j\omega\mu} = \frac{\tilde{E}}{\bar{\eta}} & z > 0 \\ -j\omega\mu & \\ +\bar{\gamma}\bar{B}e^{+\bar{\gamma}z} = -\frac{\tilde{E}}{\bar{\eta}} & z < 0 \\ -j\omega\mu & \end{cases}$$

$$\therefore \tilde{E} = \pm \bar{\eta} \tilde{H} \text{ where } \bar{\eta} = \frac{j\omega\mu}{\bar{\gamma}}$$

$$\bar{\gamma} = \sqrt{j\omega\mu(\sigma + j\omega\epsilon)}$$

$$\therefore \bar{\eta} = \sqrt{\frac{j\omega\mu}{\sigma + j\omega\epsilon}}$$

Goddard ECE329  
Lectures 21-24

37

$$\bar{\eta}^2 = |\bar{\eta}|^2 e^{j2\tau} = \frac{j\omega\mu(\sigma - j\omega\epsilon)}{\sigma^2 + (\omega\epsilon)^2} = \frac{\omega\mu(\omega\epsilon + j\sigma)}{\sigma^2 + (\omega\epsilon)^2}$$

$$\therefore \tau = \frac{1}{2} \tan^{-1} \left( \frac{\sigma}{\omega\epsilon} \right)$$

## Propagation in Dielectric

- For a uniform plane wave with  $f=10^6$  Hz in a nonmagnetic medium ( $\mu=\mu_0$ ), the propagation constant is:  $\gamma=0.05+0.1j$  m<sup>-1</sup>. Find:

- Distance for field to attenuate by e<sup>-1</sup>
- Distance for field to change phase by 1 rad
- Distance that constant phase moves in 1μs
- The ratio of |E| to |H|
- The phase difference between E and H

38

Goddard ECE329  
Lectures 21-24

From D4.8 (p249) of old book

## Power flow in Dielectric

- Given  $\mu=\mu_0$  and  $\vec{H} = H_0 e^{-z} \cos(6\pi 10^7 t - \sqrt{3}z) \hat{a}_y$ , find:
  - The instantaneous power flow across  $A=1\text{m}^2$  in the  $z=0$  plane at  $t=0$ .
  - The time averaged power flow across  $A_{@z=0}$
  - The time averaged power flow across  $A_{@z=1}$

Goddard ECE329  
Lectures 21-24

From D4.9 (p249) of old book

39

## Perfect Dielectric Material

Definition of a PERFECT dielectric:

$$\sigma = 0$$

Propagation Constant:

$$\bar{\gamma} = \sqrt{j\omega\mu(\sigma + j\omega\epsilon)}$$

$$\bar{\gamma} = j\omega\sqrt{\mu\epsilon}$$

40

Goddard ECE329  
Lectures 21-24

## Perfect Dielectric Material

$$\bar{\gamma} = j\omega\sqrt{\mu\epsilon}$$

$$\bar{\gamma} = \alpha + j\beta$$

$$\alpha = 0$$

NO ATTENUATION

$$\beta = \omega\sqrt{\mu\epsilon}$$

$$v_p = \frac{\omega}{\beta} = \frac{1}{\sqrt{\mu\epsilon}}$$

Speed of wave  
is less than  
in free space:

$$v_p = \frac{1}{\sqrt{\mu\epsilon}} = \frac{1}{\sqrt{\mu_0\mu_r\epsilon_0\epsilon_r}} = \frac{c}{\sqrt{\mu_r\epsilon_r}}$$

41

Goddard ECE329  
Lectures 21-24

## Perfect Dielectric Material

$$\bar{\eta} = \sqrt{\frac{j\omega\mu}{\sigma + j\omega\epsilon}} = \sqrt{\frac{\mu}{\epsilon}} \quad \text{Is a REAL number}$$

$$\bar{\eta} = |\bar{\eta}| e^{j\tau}$$

$$\tau = 0$$

E and H are IN PHASE

$$|\bar{\eta}| = \sqrt{\frac{\mu}{\epsilon}} = \sqrt{\frac{\mu_0\mu_r}{\epsilon_0\epsilon_r}} = \eta_0 \sqrt{\frac{\mu_r}{\epsilon_r}}$$

Impedance is different than  
free space - could be greater  
or less, depending on material

42

Goddard ECE329  
Lectures 21-24

## Finding parameters

- Given  $\mu = \mu_0$  and  $\vec{E} = 10 \cos(3\pi 10^7 t - 0.2\pi x) \hat{a}_z$ , find:
  - The frequency
  - The wavelength
  - The phase velocity
  - The relative permittivity
  - The associated  $\mathbf{H}$  field

43

Goddard ECE329  
Lectures 21-24

From P4.18 (p275) of old book

## Imperfect Dielectric

Definition:  $\sigma \neq 0$

But material does not conduct enough to really be considered a conductor

So, how much conductivity is "enough"?

Look at the loss tangent:  

$$\frac{\sigma}{\omega\epsilon}$$
 → conductivity  

$$\omega\epsilon$$
 → dielectric

44

Goddard ECE329  
Lectures 21-24


## Imperfect Dielectric

$$\frac{\sigma}{\omega\epsilon} \ll 1$$

Official math definition for what constitutes an imperfect dielectric (small loss tangent)

Also valid definitions:

$$\begin{cases} \psi \approx 90^\circ \\ \alpha \ll \beta \end{cases}$$



Very important definition


$$\frac{\partial^2 \tilde{E}_x}{\partial z^2} = j\omega\mu(\sigma + j\omega\epsilon)\tilde{E}_x$$

Tells which term is dominant

45

Goddard ECE329  
Lectures 21-24

## Behaves like a Dielectric or Conductor depending on $\omega$



46

Goddard ECE329  
Lectures 21-24

## Imperfect Dielectric: How is it different from perfect dielectric?

Only important difference: There is attenuation in an imperfect dielectric

$$\alpha \neq 0$$


$$\alpha \approx \frac{\sigma}{2} \sqrt{\frac{\mu}{\epsilon}}$$

Everything else is the same as in a perfect dielectric:

$$\beta \approx \omega \sqrt{\mu\epsilon} \quad v_p = \frac{\omega}{\beta} = \frac{1}{\sqrt{\mu\epsilon}} \quad \lambda = \frac{2\pi}{\beta}$$


Pretty good approximation as long as  $\frac{\sigma}{\omega\epsilon} < 0.1$

Goddard ECE329  
Lectures 21-24



48

Goddard ECE329  
Lectures 21-24



## Good Conductor

### Propagation Constant

$$\bar{\gamma} = \sqrt{j\omega\mu(\sigma + j\omega\epsilon)} \approx \sqrt{j\omega\mu\sigma} \\ = \sqrt{j}\sqrt{\omega\mu\sigma}$$

Warning: math trick  $\sqrt{j} = \frac{1+j}{\sqrt{2}}$

$$\bar{\gamma} = \sqrt{\frac{\omega\mu\sigma}{2}}(1+j) = \alpha + j\beta$$

$$\alpha = \beta = \sqrt{\frac{\omega\mu\sigma}{2}}$$

49

Goddard ECE329  
Lectures 21-24

## Good Conductor

### Complex Impedance

$$\bar{\eta} = \sqrt{\frac{j\omega\mu}{\sigma + j\omega\epsilon}} \approx \sqrt{\frac{j\omega\mu}{\sigma}} \\ = \sqrt{j}\sqrt{\frac{\omega\mu}{\sigma}}$$

$$\bar{\eta} = \frac{1+j}{\sqrt{2}} \sqrt{\frac{\omega\mu}{\sigma}} = (1+j)\sqrt{\frac{\omega\mu}{2\sigma}}$$

$$|\bar{\eta}| = \sqrt{\frac{\omega\mu}{\sigma}}$$

$$\tau = \pi/4$$

E and H are 45 deg  
out of phase

50

Goddard ECE329  
Lectures 21-24

## Good Conductor: Skin Depth

$\alpha$  tells us how far the E and H fields can propagate into a good conductor

In a conductor,  $\alpha$ =LARGE, so fields drop off in a short distance

SKIN DEPTH = Distance that the field strength is attenuated by  $e^{-1}$

$$\delta = \frac{1}{\alpha} = \sqrt{\frac{2}{\omega\mu\sigma}}$$

$$\text{Or } \delta = \frac{1}{\alpha} = \sqrt{\frac{1}{\pi f \mu \sigma}} \quad \text{Using } \omega = 2\pi f$$

Goddard ECE329  
Lectures 21-24

51

## Skin Depth




FIGURE 4-10  
Relative magnitude of electric field E or current density J ( $= \alpha E$ ) as a function of depth of penetration  $\delta$  for a plane wave traveling in  $x$  direction into conducting medium. The abscissa gives the penetration distance  $x$  and is expressed in 1/e depths ( $\delta$ ). The wavelength in the conductor equals  $2\pi\delta$ .

52

## Challenge Question: Material characteristics

- In what type of material would you expect dispersion (velocity depends on frequency)?

- free space
- perfect dielectric
- imperfect dielectric
- good conductor
- perfect conductor

## Perfect Conductor

$$\sigma = \infty$$

$$\alpha = \omega\sqrt{\frac{\mu\epsilon}{2}} \left( \sqrt{1 + \left( \frac{\sigma}{\omega\epsilon} \right)^2} - 1 \right)^{1/2}$$

$$\alpha = \infty$$

$$\delta = 0$$

Infinite attenuation

Means that neither E or H can propagate into a perfect conductor

NO TIME-VARYING FIELDS (E or H) CAN EXIST IN  
A PERFECT CONDUCTOR!!!

Goddard ECE329  
Lectures 21-24

53

54

Goddard ECE329  
Lectures 21-24

LG's question

## Finding parameters

- For a uniform plane wave with  $f=10^5$  Hz in a good conductor, the field is attenuated by  $e^{-\pi}$  in 2.5m. Find the following:
  - Distance for a  $2\pi$  phase change if  $f=10^5$  Hz
  - Distance a constant phase plane travels in  $1\mu\text{s}$  for  $f=10^5$  Hz
  - Distance a constant phase plane travels in  $1\mu\text{s}$  for  $f=10^4$  Hz assuming the material properties are the same as at  $f=10^5$  Hz

Goddard ECE329  
Lectures 21-24

From D4.11 (p254) of old book

55

## Lecture 21-23 Summary

| Perfect Dielectric   | Imperfect Dielectric   |
|--|--|
| Definition: $\sigma = 0$                                     | Definition: $\sigma / \omega \epsilon \ll 1$                       |
| Attenuation: $\alpha = 0$                                    | Attenuation: $\alpha \approx \sigma / 2\sqrt{\mu/\epsilon}$        |
| Speed: $v_p = c / \sqrt{\mu_r \epsilon_r} \leq c$            | Speed: $v_p \approx c / \sqrt{\mu_r \epsilon_r} \leq c$            |
| $\mathbf{E}, \mathbf{H}$ In Phase: $\tau = 0$                | $\mathbf{E}, \mathbf{H}$ In Phase: $\tau \approx 0$                |
| Impedance: $ \bar{\eta}  = \eta_0 \sqrt{\mu_r / \epsilon_r}$ | Impedance: $ \bar{\eta}  \approx \eta_0 \sqrt{\mu_r / \epsilon_r}$ |
| Good Conductor   | Perfect Conductor  |
| Definition: $\sigma / \omega \epsilon \gg 1$                 | Definition: $\sigma \rightarrow \infty$                            |
| Attenuation: $\alpha \approx \sqrt{\omega \mu \sigma / 2}$   | Attenuation: $\alpha \rightarrow \infty$                           |
| Speed: $v_p \approx \sqrt{2\omega / \sigma\mu}$              | Speed: $v_p \rightarrow 0$   |
| $\mathbf{E}, \mathbf{H}$ 45° Phase: $\tau \approx \pi/4$     |  |
| Impedance: $ \bar{\eta}  \approx \sqrt{\omega \mu / \sigma}$ | Impedance: $ \bar{\eta}  \rightarrow 0$                            |

Goddard ECE329  
Lectures 21-24

56

## Lecture 24 Section 1.4

### Polarization

Adapted from Prof. Cunningham's Notes

57

Goddard ECE329  
Lectures 21-24

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited



## Definition of Polarization

- Describes the “tip” of the time-varying  $\mathbf{E}$  field vector for a particular point in space as it varies in time
- $\mathbf{J} = -\mathbf{J}_{S0} \mathbf{a}_x$  example
  - Field with only one component is always linearly polarized

$$E_x(z, t) = \frac{\eta_0 J_{S0}}{2} \cos(\omega t \mp \beta z)$$

58

## Web Demo



<http://www.enzim.hu/~szia/cddemo/edemo0.htm>

Goddard ECE329  
Lectures 21-24

59

## How do we treat this mathematically?

Say we have two superimposed fields

- Propagating in same direction
- Possibly out of phase
- Possibly oriented out of plane with each other

How can we tell if the combined wave will be:


- Linear
- Circular
- Elliptical

Goddard ECE329  
Lectures 21-24

60

## Linear Polarization

Plane in space perpendicular to propagation direction



The tip of the E-field vector traces out a straight line  
DIRECTION: Constant  
MAGNITUDE: Changes w/ time

How do we get this mathematically?

61

Goddard ECE329  
Lectures 21-24

## Linear Polarization

Given two linearly polarized vector fields


$$\vec{E}_1 = E_1 \cos(\omega t + \phi) \hat{a}_x \quad \vec{E}_1 \text{ is horizontal linear polarization (green)}$$

$$\vec{E}_2 = \pm E_2 \cos(\omega t + \phi) \hat{a}_y \quad \vec{E}_2 \text{ is vertical linear polarization (red)}$$

If the vectors are IN PHASE or 180° apart,  $\vec{E}_1 + \vec{E}_2$  will also be linear polarization

$$\vec{E}_1 + \vec{E}_2 = \cos(\omega t + \phi)(E_1 \hat{a}_x \pm E_2 \hat{a}_y)$$

Magnitude changes Direction is constant



$$\alpha = \pm \tan^{-1} \left( \frac{E_2}{E_1} \right)$$


Polarization ANGLE depends on relative magnitudes of  $E_1$  and  $E_2$

62

Goddard ECE329  
Lectures 21-24

## Circular Polarization

Plane in space perpendicular to propagation direction



The tip of the E-field vector traces out a circle  
DIRECTION: Changes with time  
MAGNITUDE: Constant

How do we get this mathematically?

63

Goddard ECE329  
Lectures 21-24

## Circular Polarization

Given two linearly polarized vector fields

$$\vec{E}_1 = E_0 \cos(\omega t + \phi) \hat{a}_x \quad \vec{E}_1 \text{ is horizontal linear polarization (green)}$$

$$\vec{E}_2 = E_0 \sin(\omega t + \phi) \hat{a}_y \quad \vec{E}_2 \text{ is vertical linear polarization (red)}$$

The vectors have EQUAL MAGNITUDES

The vectors are OUT OF PHASE by  $\pi/2$

The vectors are PERPENDICULAR


ALL THREE CONDITIONS MUST BE MET  
for  $\vec{E}_1 + \vec{E}_2$  to be circular polarization

64


Goddard ECE329  
Lectures 21-24

## How to tell: Left or Right Handed Circular Polarization

Method 1: Left/right thumb points in **propagation** direction




"Right-Hand" Polarized  
(cw as seen by source)



"Left-Hand" Polarized  
(ccw as seen by source)

LHCP if moving in  $-a_z$



65

Goddard ECE329  
Lectures 21-24

## How to tell: Left or Right Handed Circular Polarization

Method 2: It's right handed if  
Ahead  $\hat{E}$  x Behind  $\hat{E}$  is in propagation direction

$$\vec{E}_1 = E_0 \cos(\omega t \pm \beta z) \hat{x} \quad \text{Ahead}$$


$$\vec{E}_2 = E_0 \sin(\omega t \pm \beta z) \hat{y}$$

$$= E_0 \cos(\omega t \pm \beta z - \frac{\pi}{2}) \hat{y} \quad \text{Behind}$$

It is behind by  $\pi/2$   
because  $\omega t$  needs to be  
 $\pi/2$  larger to be at the  
same part of the wave

$\hat{E}_1 \times \hat{E}_2 = \hat{z}$   
so RHC if  
moving in  $+a_z$

else LHC if  
moving in  $-a_z$



66

Goddard ECE329  
Lectures 21-24

## How to tell: Left or Right Handed Circular Polarization

Method 3: It's right handed if  $\text{Re}[\hat{\vec{E}}] \times \text{Im}[-\hat{\vec{E}}]$  is in propagation direction

$$\vec{E}_1 = E_0 \cos(\omega t \pm \beta z) \hat{x} \quad \text{Ahead}$$

$$\vec{E}_2 = E_0 \cos(\omega t \pm \beta z - \frac{\pi}{2}) \hat{y} \quad \text{Behind}$$

$$\tilde{\vec{E}} = \vec{E}_1 + \vec{E}_2 = E_0 e^{\pm j\beta z} \hat{x} + E_0 e^{\pm j\beta z} e^{-j\frac{\pi}{2}} \hat{y} = E_0 e^{\pm j\beta z} (\hat{x} - j\hat{y})$$

$$\hat{\vec{E}} \equiv \hat{x} - j\hat{y}$$

I made up this notation.  
note it is not a unit vector

$\text{Re}[\hat{\vec{E}}] = \hat{x}$  gives the Ahead field

$\text{Im}[-\hat{\vec{E}}] = \hat{y}$  gives the Behind field


67

Goddard ECE329  
Lectures 21-24

## Elliptical Polarization

Most general: two combined linearly polarized waves will result in an elliptically polarized wave - if the conditions for linear or circular are not satisfied.

Plane in space perpendicular to propagation direction



The tip of the E-field vector traces out an ellipse

DIRECTION: Changes with time  
MAGNITUDE: Changes

68

Goddard ECE329  
Lectures 21-24

## Sum of two fields

- For  $\mathbf{E}_1 = E_0 \cos(2\pi \times 10^8 t - 2\pi z) \mathbf{a}_x$ , and  $\mathbf{E}_2 = E_0 \cos(2\pi \times 10^8 t - 3\pi z) \mathbf{a}_y$ , find the polarization of  $\mathbf{E}_1 + \mathbf{E}_2$  at the following points:

- (3, 4, 0)
- (3, -2, 0.5)
- (-2, 1, 1)
- (-1, -3, 0.2)

69

Goddard ECE329  
Lectures 21-24

From D3.17 (p 184) of old book

## Challenge Question: Forming Circular Polarization

- For what value of  $\phi$ , will the following fields add to produce **right** handed circular polarization:

$$\begin{aligned}\mathbf{E}_1 &= E_0 \cos(2\pi \times 10^8 t + 2\pi z + \pi/3) \mathbf{a}_x, \\ \mathbf{E}_2 &= E_0 \cos(2\pi \times 10^8 t + 2\pi z + \phi) \mathbf{a}_y\end{aligned}$$

- $\pi/3$
- $-\pi/3$
- $\pi/6$
- $-\pi/6$
- $5\pi/6$

70

Goddard ECE329  
Lectures 21-24

LG's question

## Writing linearly polarized as a sum of circular polarization

- Rewrite  $\mathbf{E} = E_0 \cos(\omega t + \beta z) \mathbf{a}_x$  as a sum of circular polarized fields.

71

Goddard ECE329  
Lectures 21-24

From Problem 3.35a (p 203) of old book

## Lecture 24 Summary

- Polarization describes the "tip" of  $\mathbf{E}(t)$
- Linear
  - Direction is \_\_\_\_\_
  - Magnitude is \_\_\_\_\_
- Circular
  - Direction \_\_\_\_\_
  - Magnitude is \_\_\_\_\_
- Elliptical
  - Direction \_\_\_\_\_
  - Magnitude \_\_\_\_\_
- Next up: Section 5.6: Wave reflection



72

Goddard ECE329  
Lectures 21-24

## Lectures 25-26

### Section 5.6


### Reflection and Transmission Standing Waves

1

Goddard ECE329  
Lectures 25-26

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

### Normal incidence plane wave



We will analyze the case  $J_s=0$  at  $z=0$  (no applied surface current).  
For the case  $J_s \neq 0$ , use superposition of the  $J_s=0$  case with the answer for waves generated by a current sheet.

Goddard ECE329  
Lectures 25-26


2

### Reflected and Transmitted Waves are Generated

3

Goddard ECE329  
Lectures 25-26

### Apply Boundary Conditions



4

Goddard ECE329  
Lectures 25-26

### Apply Boundary Conditions

5

Goddard ECE329  
Lectures 25-26

### Solve the Equations

$$\begin{aligned} \bar{E}_1^+ + \bar{E}_1^- &= \bar{E}_2^+ \\ \frac{\bar{\eta}_2}{\bar{\eta}_1} (\bar{E}_1^+ - \bar{E}_1^-) &= \bar{E}_2^+ \end{aligned}$$

Reflection Coefficient:

$$\therefore \Gamma = \frac{\bar{E}_1^-}{\bar{E}_1^+} = \frac{\bar{\eta}_2 - \bar{\eta}_1}{\bar{\eta}_1 + \bar{\eta}_2}$$


$$\begin{aligned} \tau &= \frac{\bar{E}_2^+}{\bar{E}_1^+} = \frac{\bar{E}_1^+ + \bar{E}_1^-}{\bar{E}_1^+} = 1 + \Gamma \\ \text{Transmission Coefficient: } \tau &= \frac{\bar{E}_2^+}{\bar{E}_1^+} = 1 + \Gamma = \frac{2\bar{\eta}_2}{\bar{\eta}_1 + \bar{\eta}_2} \end{aligned}$$

6

Goddard ECE329  
Lectures 25-26

## Challenge Question: Special cases

- If  $\eta_2 = \eta_1$ , we expect:



- (a)  $\Gamma=0, \tau=1$  (0% reflected, 100% transmitted)  
 (b)  $\Gamma=0, \tau=-1$  (0% reflected, 100% transmitted)  
 (c)  $\Gamma=1, \tau=0$  (100% reflected, 0% transmitted)  
 (d)  $\Gamma=-1, \tau=0$  (100% reflected, 0% transmitted)  
 (e) cannot be determined


Goddard ECE329  
Lectures 25-26

LG's question

7

## Challenge Question: Special cases

- If medium 2 is a perfect conductor, we expect:



- (a)  $\Gamma=0, \tau=1$  (0% reflected, 100% transmitted)  
 (b)  $\Gamma=0, \tau=-1$  (0% reflected, 100% transmitted)  
 (c)  $\Gamma=1, \tau=0$  (100% reflected, 0% transmitted)  
 (d)  $\Gamma=-1, \tau=0$  (100% reflected, 0% transmitted)  
 (e) cannot be determined

Goddard ECE329  
Lectures 25-26

LG's question

8

## Special Cases of Reflection/Transmission

$$\Gamma \equiv \frac{\bar{E}_1^-}{\bar{E}_1^+} = \frac{\eta_2 - \eta_1}{\eta_2 + \eta_1}, \tau \equiv \frac{\bar{E}_2^+}{\bar{E}_1^+} = 1 + \Gamma$$

- Impedance matched:  $\eta_2 = \eta_1$ , then  $\Gamma=0, \tau=1$   
 – No reflection, entire wave is transmitted
- Perfect dielectrics:  $\sigma_1 = \sigma_2 = 0$ , then  $\Gamma$  and  $\tau$  are real since  $\eta_1$  and  $\eta_2$  are real
- Perfect conductor for medium 2:  $\eta_2 \rightarrow 0$ , then  $\Gamma=-1, \tau=0$   
 – No transmission, entire wave is reflected. If medium 1 is a perfect dielectric, a standing wave is set up there since reflected wave perfectly cancels input wave at many nodes:  $E(z=0)=0$  always, but if  $\sigma_1=0$ , then  $E(z=m\lambda/2)=0$  also



9

Goddard ECE329  
Lectures 25-26

## Standing Waves

- The reflection from a PC gives  $\Gamma=-1$
- If region 1 is a perfect dielectric, we get standing waves whereby the input and reflected wave add destructively at specific points in space (vs. travelling waves  $f(t \pm z/v)$ )

$$\begin{aligned}\tilde{E}_{1x\ total}(z) &= \bar{E}_1^+ e^{-\beta_1 z} + \bar{E}_1^- e^{+\beta_1 z} = \bar{E}_1^+ (e^{-j\beta_1 z} - e^{+j\beta_1 z}) = \bar{E}_1^+ (-2j \sin(\beta_1 z)) \\ \tilde{H}_{1y\ total}(z) &= \frac{1}{\eta_1} (\bar{E}_1^+ e^{-\beta_1 z} - \bar{E}_1^- e^{+\beta_1 z}) = \frac{\bar{E}_1^+}{\eta_1} (e^{-j\beta_1 z} + e^{+j\beta_1 z}) = \frac{\bar{E}_1^+}{\eta_1} 2 \cos(\beta_1 z) \\ \tilde{E}(z, t) &= \hat{x} \operatorname{Re}[\bar{E}_1^+ (-2j \sin(\beta_1 z)) e^{i\omega t}] = \hat{x} |\bar{E}_1^+| \sin(\beta_1 z) \sin(\omega t + \angle \bar{E}_1^+) \\ \tilde{H}(z, t) &= \hat{y} \operatorname{Re}[\frac{\bar{E}_1^+}{\eta_1} 2 \cos(\beta_1 z) e^{i\omega t}] = \hat{y} \frac{2}{\eta_1} |\bar{E}_1^+| \cos(\beta_1 z) \cos(\omega t + \angle \bar{E}_1^+)\end{aligned}$$



10

Goddard ECE329  
Lectures 25-26

## Standing Waves: on average, the net energy transport is zero

Show  $\langle \mathbf{S} \rangle = \langle \mathbf{E} \times \mathbf{H} \rangle = 0$ . Online notes use phasors. Here we'll use  $\mathbf{E}$  and  $\mathbf{H}$  explicitly (still assume  $\sigma_1=0$ ).

$$\begin{aligned}\bar{E}(z, t) &= 2|\bar{E}_1^+| \sin(\beta_1 z) \sin(\omega t + \angle \bar{E}_1^+) \hat{x} \\ \bar{H}(z, t) &= \frac{2}{\eta_1} |\bar{E}_1^+| \cos(\beta_1 z) \cos(\omega t + \angle \bar{E}_1^+) \hat{y} \\ \bar{S}(z, t) &= \frac{4}{\eta_1} |\bar{E}_1^+|^2 \sin(\beta_1 z) \cos(\beta_1 z) \sin(\omega t + \angle \bar{E}_1^+) \cos(\omega t + \angle \bar{E}_1^+) \hat{z} \\ &= \frac{1}{\eta_1} |\bar{E}_1^+|^2 \sin(2\beta_1 z) \sin(2(\omega t + \angle \bar{E}_1^+)) \hat{z} \quad \therefore \langle \bar{S}(z, t) \rangle = 0\end{aligned}$$

since  $\sin(2\omega t)$  is periodic

At any moment in time,  
there is energy transport,  
but it averages to zero.

11

Goddard ECE329  
Lectures 25-26

## Incident wave induces surface current on PC that radiates the reflected wave

$\mathbf{H}$  is discontinuous at  $z=0$ ,  $\mathbf{H}_{t2}=0$  but  $\mathbf{H}_{t1}$  oscillates:

$$\bar{H}(z, t) = \hat{y} \frac{2}{\eta_1} |\bar{E}_1^+| \cos(\omega t + \angle \bar{E}_1^+)$$

Thus, the BC's imply a surface current is induced at  $z=0$ :

$$\bar{J}_s(t) = \hat{x} \frac{2}{\eta_1} |\bar{E}_1^+| \cos(\omega t + \angle \bar{E}_1^+)$$

This surface current is now a source that can radiate a wave away from the plane in  $-a_z$  (i.e. the reflected wave):

$$\bar{E}_{\text{reflected}}(z, t) = (-\hat{x}) \frac{\eta_1}{2} J_s(t - \frac{z}{v_p}) = -\hat{x} |\bar{E}_1^+| \cos(\omega t + \beta z + \angle \bar{E}_1^+)$$


which is precisely the wave we found when we used  $\Gamma=-1$ .

The part that radiates into  $+a_z$  perfectly cancels out the incident field for  $z>0$  which gives us  $\mathbf{E}=0$  in the PC as expected.


Slight complication:  $\mathbf{J}$  was created by  $\mathbf{J}=\sigma \mathbf{E}$ , but  $\mathbf{E}=0$  at the PC. Note  $\sigma=\infty$ .

12

Goddard ECE329  
Lectures 25-26



## Lectures 25-26 Summary



Next: Transmission lines: Section 6.5 & Chapter 7

Goddard ECE329  
Lectures 25-26

13

# ECE 329

## Lectures 27-30

### Section 6.5 and Chapter 7

#### Transmission Lines

#### Time Domain Analysis


Adapted from Prof. Cunningham's Notes

1

Goddard ECE329  
Lectures 27-30

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

#### Starting Point: Uniform Plane Wave




2

Goddard ECE329  
Lectures 27-30

#### Starting Point: Uniform Plane Wave


- Consider  $\mathbf{E}$  and  $\mathbf{H}$  that are
  - Perpendicular to each other
  - Perpendicular to the direction of propagation
  - Magnitude is constant ("uniform") in the plane perpendicular to the propagation direction
  - And for perfect dielectric media:
    - $\mathbf{E}$  and  $\mathbf{H}$  are in phase
    - No attenuation in  $z$ -direction



Goddard ECE329  
Lectures 27-30

#### Parallel Plate Transmission Line

Imagine a rectangular box made of perfect conductors on the upper and lower surfaces, filled by perfect dielectric medium




- If we place conducting sheets in the path of the uniform plane wave, some of the wave enters the box and is guided by it

4

Goddard ECE329  
Lectures 27-30

#### Parallel Plate Transmission Line




Goddard ECE329  
Lectures 27-30

Cross section of the transmission line so wave is propagating into the page

5

#### Consider boundary conditions



The  $\mathbf{E}$  and  $\mathbf{H}$  fields inside the transmission line induce charge and current on the upper and lower surfaces  
Apply BC's on  $D_n$  and  $H_t$  to find  $\rho_s$  and  $J_s$  respectively


$$|\rho_s| = |\epsilon E_x|$$

$$|J_s| = |H_y|$$

6

Goddard ECE329  
Lectures 27-30

## TL Voltage




$$V(z, t) = (d) E_x(z, t)$$

7

Goddard ECE329  
Lectures 27-30

## TL Current – Charges on both plates move to the right




$$I(z, t) = w H_y(z, t)$$

8

Goddard ECE329  
Lectures 27-30

## TL Power



$$P(z, t) = \int_S (\vec{E} \times \vec{H}) \cdot d\vec{S} = \int_{x=0}^{x=d} \int_{y=0}^{y=w} V \cdot \frac{I}{w} dx dy$$


$$P(z, t) = V(z, t) I(z, t)$$

same as in circuit theory

9

Goddard ECE329  
Lectures 27-30

## Converting $E \leftrightarrow V$ and $H \leftrightarrow I$




Find the power crossing this transverse cross section if  
(a)  $E = 300\pi$  V/m, (b)  $H = 7.5$  A/m, (c)  $V = 4\pi$  V, (d)  $I = 0.5$  A

10

Goddard ECE329  
Lectures 27-30

From D6.1 (p371) of old book

## Another look at transverse plane of TL



$V(z, t)$  and  $I(z, t)$  can be used to describe the state of the transmission line instead of  $E_x(z, t)$  and  $H_y(z, t)$

11

Goddard ECE329  
Lectures 27-30

## Transmission Line Equations

For plane waves in perfect dielectric:

$$\begin{cases} \frac{\partial E_x}{\partial z} = -\frac{\partial B_y}{\partial t} = -\mu \frac{\partial H_y}{\partial t} \\ \frac{\partial H_y}{\partial z} = -\frac{\partial E_x}{\partial t} = -\epsilon \frac{\partial E_x}{\partial t} \end{cases}$$

But in the transmission line:

$$\begin{cases} E_x(z, t) = \frac{V(z, t)}{d} \\ H_y(z, t) = \frac{I(z, t)}{w} \end{cases}$$

12

Goddard ECE329  
Lectures 27-30

## Transmission Line Equations

Substituting...

$$\begin{cases} \frac{\partial V}{\partial z} = -\left(\frac{\mu d}{w}\right) \frac{\partial I}{\partial z} \\ \frac{\partial I}{\partial z} = -\left(\frac{\sigma w}{d}\right) V \end{cases}$$


These are the transmission line equations!!

- They describe wave propagation along the TL in terms of currents and voltages
- It is just another way of stating Maxwell's Eqns

13

Goddard ECE329  
Lectures 27-30

## Circuit Parameters



Rewrite the TL Equation using circuit parameters

$$L = \frac{L}{z} = \frac{\text{Inductance}}{\text{Length}} = \frac{\text{Flux / Current}}{\text{Length}} = \frac{\psi / I}{z}$$

$$= \frac{B_y z d / H_y w}{z} = \frac{B_y d}{H_y w} = \frac{\mu H_y d}{H_y w} = \frac{\mu d}{w}$$

$$C = \frac{C}{z} = \frac{\text{Capacitance}}{\text{Length}} = \frac{\text{Charge/Voltage}}{\text{Length}} = \frac{Q / V}{z}$$

$$= \frac{\rho z w / E_x d}{z} = \frac{\rho w}{E_x d} = \frac{\epsilon E_x w}{E_x d} = \frac{\epsilon w}{d}$$

14

Goddard ECE329  
Lectures 27-30

## Transmission Line Equation

$$\frac{\partial V}{\partial z} = -L \frac{\partial I}{\partial z}$$

$$\frac{\partial I}{\partial z} = -C \frac{\partial V}{\partial z}$$

For lossless transmission lines  
Perfect dielectric filling  
Perfect conductor outer shell


Don't forget that L & C are related:

$$\mathcal{LC} = \mu \epsilon$$

15

Goddard ECE329  
Lectures 27-30

## Distributed Circuit



One small slice of the transmission line would have a finite inductance and capacitance.


If we put our small slices together, end to end, to make a whole transmission line, the inductance and capacitance would be distributed over the whole length of the TL.

How do we represent a distributed circuit element?

16

Goddard ECE329  
Lectures 27-30

## Flip the parallel plate for TL (ground the bottom plate)




17

Goddard ECE329  
Lectures 27-30

## Distributed Circuit

One slice of the TL:



$$V(z + \Delta z) - V(z) = -L \frac{\partial I}{\partial z}$$

$$I(z) - I(z + \Delta z) = C \frac{\partial V}{\partial z}$$

$$\therefore \frac{\partial V}{\partial z} = -L \frac{\partial I}{\partial z}$$

$$\therefore \frac{\partial I}{\partial z} = -C \frac{\partial V}{\partial z}$$


These are the same as the TL equations so this is the equivalent circuit for the TL

18


Goddard ECE329  
Lectures 27-30

## Distributed Circuit

One slice of the TL:



The entire TL:




Goddard ECE329  
Lectures 27-30

19

## Characteristic Impedance

A more convenient way of representing the distributed circuit




$$Z_0 = \sqrt{\frac{L}{C}} = \sqrt{\frac{|V(z,t)|}{|I(z,t)|}}$$

$$v_p = \frac{1}{\sqrt{\mu\epsilon}} = \frac{1}{\sqrt{LC}}$$

20

Goddard ECE329  
Lectures 27-30

## Challenge Question: Transmission Lines



- For waves propagating down transmission lines, which of the following is **false**:
- the impedances  $Z_0$  and  $\eta_0$  are equal
  - the propagation speed is  $\leq c$
  - the propagation speed in two lines can be different even if the impedance  $Z_0$  is the same
  - in steady state, the TL acts like plain wires
  - the fields store energy distributed among the inductive and capacitive segments of the TL

Goddard ECE329  
Lectures 27-30

LG's question

21

## Designing coaxial cables

Design a  $50\Omega$  coaxial cable if  $\epsilon_r=2.56$  and  $a=1\text{cm}$ , i.e. find b.

22

Goddard ECE329  
Lectures 27-30

From D6.2a (p372) of old book

## ECE 329 Lecture 28

TL Terminated by Resistive Load  
Bounce Diagram

Adapted from Prof. Cunningham's Notes

23

Goddard ECE329  
Lectures 27-30

## Solution to TL Equation

We can solve the TL Equations the same way that we solved the wave equation for uniform plane waves in free space:

$$V(z,t) = Af\left(t - \frac{z}{v_p}\right) + Bg\left(t + \frac{z}{v_p}\right)$$

$$I(z,t) = \frac{1}{Z_0} \left[ Af\left(t - \frac{z}{v_p}\right) - Bg\left(t + \frac{z}{v_p}\right) \right]$$

Solution is a superposition of traveling waves  
- one going in  $+z$  direction  
- one going in  $-z$  direction

24

Goddard ECE329  
Lectures 27-30

## Simplified shorthand notation

$$V(z,t) = V^+(t - \frac{z}{v_p}) + V^-(t + \frac{z}{v_p})$$

$$I(z,t) = \frac{1}{Z_0} \left[ V^+(t - \frac{z}{v_p}) - V^-(t + \frac{z}{v_p}) \right]$$

Simplifying even more...

$$V = V^+ + V^-$$

$$I = \frac{1}{Z_0} (V^+ - V^-) = I^+ + I^-$$

25

Goddard ECE329  
Lectures 27-30

## Solution to TL equation

$$V = V^+ + V^-$$

$$I = \frac{1}{Z_0} (V^+ - V^-) = I^+ + I^-$$


$$I^+ = \frac{V^+}{Z_0} \quad I^- = -\frac{V^-}{Z_0}$$

Solution to TL equation is summation of traveling waves propagating in the  $+z$  or  $-z$  directions

26

Goddard ECE329  
Lectures 27-30

## Example: TL + Resistive Load




27

Goddard ECE329  
Lectures 27-30

## Example, $t=0$

$$V_0 - I^+ R_g - V^+ = 0$$

$$I^+ = \frac{V^+}{Z_0}$$



$$\tau_g V_0$$

$\tau_g$  is the injection coefficient

$$V^+ = \frac{Z_0}{R_g + Z_0} V_0$$

$$I^+ = \frac{V_0}{R_g + Z_0}$$

At  $t=0$ , a wave originates at  $z=0$  and starts to travel in the  $+z$  direction

Until the wave propagates to the end and reflects back, there is no  $V^-$  wave, and the load resistance  $R_L$  has no effect.

28

Goddard ECE329  
Lectures 27-30

## Example $t=T$

$$T = \frac{l}{v_p}$$

Time required for  $V^+$  wave to reach load end of the TL

$$V^+ + V^- = R_L (I^+ + I^-)$$

$\xrightarrow{\text{Time } T}$

$(I^+ + I^-)$   
 $(V^+ + V^-)$   
 $-$   
 $z=l$

$$V^- = V^+ \frac{R_L - Z_0}{R_L + Z_0}$$

Wave reflects to set up a “-” wave IN ADDITION TO the “+” wave

Equation 7.50a,b should say  $V^+ + V^-$  instead of  $V^+ - V^-$

29

Goddard ECE329  
Lectures 27-30

## Definition: Reflection Coefficient

Voltage Reflection Coefficient

$$\Gamma = \frac{V^-}{V^+} = \frac{R_L - Z_0}{R_L + Z_0}$$


Current Reflection Coefficient

$$\frac{I^-}{I^+} = \frac{-(V^-/Z_0)}{(V^+/Z_0)} = -\frac{V^-}{V^+} = -\Gamma$$

30

Goddard ECE329  
Lectures 27-30

## Example, $t=2T$



Reflected wave travels back towards the source, and gets there at  $t=2T$

The wave gets RE-REFLECTED at the source end and travels back toward the load as a "+" wave

The re-reflection process continues forever until steady state conditions are reached

Goddard ECE329  
Lectures 27-30

31

## Special Case TL Terminations

Short-circuited line:  $R_L=0$

$$\Gamma = \frac{V^-}{V^+} = \frac{R_L - Z_0}{R_L + Z_0} = \frac{0 - Z_0}{0 + Z_0} = -1 \quad \text{No voltage across } R_L$$

Open-circuited line:  $R_L=\infty$

$$\Gamma = \frac{V^-}{V^+} = \frac{\infty - Z_0}{\infty + Z_0} = 1 \quad \text{No current across } R_L$$


Impedance-matched line:  $R_L = Z_0$

$$\Gamma = \frac{V^-}{V^+} = \frac{Z_0 - Z_0}{Z_0 + Z_0} = 0 \quad \text{No reflection at } R_L$$

Goddard ECE329  
Lectures 27-30

32

## Bounce Diagram



First step: Calculate  $V^+$ ,  $I^+$ ,  $\Gamma_{load}$ ,  $\Gamma_{source}$

$$V^+ = V_0 \frac{Z_0}{R_s + Z_0} = 100 \frac{60}{40 + 60} = 60V \quad \Gamma_{load} = \frac{R_L - Z_0}{R_L + Z_0} = \frac{120 - 60}{120 + 60} = \frac{1}{3}$$


$$I^+ = \frac{V^+}{Z_0} = \frac{60}{60} = 1A \quad \Gamma_{source} = \frac{R_s - Z_0}{R_s + Z_0} = \frac{40 - 60}{40 + 60} = -\frac{1}{5}$$

Second step: Construct 2 bounce diagrams  
(Voltage and Current)


33

Goddard ECE329  
Lectures 27-30

### Voltage



### Current




Goddard ECE329  
Lectures 27-30

34

### Voltage

### Current




35

Goddard ECE329  
Lectures 27-30







### Voltage

### Current



36

Goddard ECE329  
Lectures 27-30



## ECE 329 Lecture 29

### Algebra of the Bounce Diagram

Adapted from Prof. Cunningham's Notes

43

Goddard ECE329  
Lectures 27-30

### Steady State

If  $\Gamma_s \Gamma_l < 1$ , then eventually, the magnitude of the reflections will die down, and the voltage and current reach constant, steady state values

$$\begin{cases} V_{ss}^+ = 60(1 - \frac{1}{15} + \frac{1}{15^2} + \dots) & \text{Sum of all + waves} = 56.25V \\ V_{ss}^- = 20(1 - \frac{1}{15} + \frac{1}{15^2} + \dots) & \text{Sum of all - waves} = 18.75V \\ I_{ss}^+ = l(1 - \frac{1}{15} + \frac{1}{15^2} + \dots) & \text{Sum of all + waves} = 0.9375A \\ I_{ss}^- = -\frac{1}{3}(1 - \frac{1}{15} + \frac{1}{15^2} + \dots) & \text{Sum of all - waves} = -0.3125A \end{cases}$$


Goddard ECE329  
Lectures 27-30

$$\sum_{n=0}^{\infty} \left(-\frac{1}{15}\right)^n = \frac{1}{1+1/15} = \frac{15}{16}$$

44

### In SS, TL Looks Like a Wire


$$V_{ss} = V_{ss}^+ + V_{ss}^- = 75V \quad I_{ss} = I_{ss}^+ + I_{ss}^- = 0.625A$$



Goddard ECE329  
Lectures 27-30

### Algebra of the Bounce Diagram

Voltage divider:



$V^-(0,t) = \Gamma_L V^+(0,t-2T)$  ← Reflected wave is the forward wave at time  $2T$  ago and multiplied by reflection coefficient  $\Gamma_L$

$$V(0,t) = V^+(0,t) + V^-(0,t) = f(t) - R_s I(0,t)$$

$$I(0,t) = I^+(0,t) + I^-(0,t) = \frac{V^+(0,t) - V^-(0,t)}{Z_0}$$

New wave is source + old wave  $2T$  ago multiplied by RT reflection coeff.  $\Gamma_L \Gamma_s$


$$V^+(0,t) = \tau_s f(t) + \Gamma_L V^+(0,t-2T)$$

46

Goddard ECE329  
Lectures 27-30

### Algebra of the Bounce Diagram

For  $f(t) = \delta(t)$ , the solution of:  $V^+(0,t) = \tau_s \delta(t) + \Gamma_s \Gamma_L V^+(0,t-2T)$   
is an impulse response:



Goddard ECE329  
Lectures 27-30

47

### Algebra of the Bounce Diagram

$$V^+(0,t) = \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n \delta(t-n2T) \equiv h^+(t)$$


$$V^-(0,t) = \Gamma_L \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n \delta(t-(n+1)2T) \equiv h^-(t)$$

For arbitrary position  $z$ , replace  $t$  with  $t \pm z/v_p$

$$V^+(z,t) = \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n \delta(t - \frac{z}{v_p} - n2T) \quad I = \frac{1}{Z_0} (V^+ - V^-)$$

$$V^-(z,t) = \Gamma_L \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n \delta(t + \frac{z}{v_p} - (n+1)2T)$$

Note: the voltage is nonzero only on the bounce lines



48

Goddard ECE329  
Lectures 27-30

## Algebra of the Bounce Diagram

For  $f(t)=\delta(t)$ , the solution was:

$$V^+(z,t) = \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n \delta(t - \frac{z}{v_p} - n2T)$$

$$V^-(z,t) = \Gamma_L \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n \delta(t + \frac{z}{v_p} - (n+1)2T)$$

$$I = \frac{1}{Z_0} (V^+ - V^-)$$

For arbitrary  $f(t)$ , convolve the solution with  $f$ :

$$V^+(z,t) = \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n f(t - \frac{z}{v_p} - n2T)$$

$$V^-(z,t) = \Gamma_L \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n f(t + \frac{z}{v_p} - (n+1)2T)$$

$$I = \frac{1}{Z_0} (V^+ - V^-)$$

Note: the voltage can be nonzero in between the bounce lines depending on the function  $f$

49

Goddard ECE329

Lectures 27-30

## Lectures 27-29 Summary

- Transmission Line Equations

$$\frac{\partial V}{\partial z} = -L \frac{\partial I}{\partial z} \quad \frac{\partial I}{\partial z} = -C \frac{\partial V}{\partial z}$$

- Characteristic impedance & Speed

$$Z_0 = \sqrt{\frac{L}{C}} = \frac{|V(z,t)|}{|I(z,t)|} \quad v_p = \frac{1}{\sqrt{\mu\epsilon}} = \frac{1}{\sqrt{LC}}$$

- Bounce Diagram

- Round Trip Equation

$$V^+(0,t) = \tau_s f(t) + \Gamma_s \Gamma_L V^+(0,t-2T) \quad V^+(z,t) = \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n f(t - \frac{z}{v_p} - n2T) \quad I = \frac{1}{Z_0} (V^+ - V^-)$$

Goddard ECE329

Lectures 27-30

$$V^-(z,t) = \Gamma_L \tau_s \sum_{n=0}^{\infty} (\Gamma_s \Gamma_L)^n f(t + \frac{z}{v_p} - (n+1)2T)$$

50

## ECE 329 Lecture 30

### TL Discontinuities

#### (Optional) TL Circuits with Reactive Elements


Adapted from Prof. Cunningham's Notes

51

Goddard ECE329

Lectures 27-30


## TL Discontinuity



52

## TL Discontinuity

What happens at the boundary between two TL's?




Assume that (+) wave hits the junction from the left

53


Goddard ECE329

Lectures 27-30

#### Before + wave hits boundary



What equations should we write for the boundary?



54

Goddard ECE329

Lectures 27-30

## Calculation Space

55

Goddard ECE329  
Lectures 27-30

## Voltage Reflection Coeff

$$\Gamma = \frac{V^-}{V^+} = \frac{Z_{02} - Z_{01}}{Z_{02} + Z_{01}}$$

Fraction of incident voltage that gets reflected back

## Voltage Transmission Coeff

$$\tau_v = \frac{V^{++}}{V^+} = \frac{V^+ + V^-}{V^+} = 1 + \frac{V^-}{V^+}$$

$$\tau_v = 1 + \Gamma$$

Fraction of incident voltage that gets transmitted through

56

Goddard ECE329  
Lectures 27-30

## Current Transmission Coeff

$$\tau_c = \frac{I^{++}}{I^+} = \frac{I^+ + I^-}{I^+} = 1 + \frac{I^-}{I^+}$$

$$\tau_c = 1 - \Gamma$$

Fraction of incident current that gets transmitted through

57

Goddard ECE329  
Lectures 27-30

## Power

$$P_{\text{incident}} = V^+ I^+$$

$$P_{\text{reflected}} = V^- I^-$$

$$P_{\text{transmitted}} = V^{++} I^{++}$$


Some of the incident power is reflected back and the rest is transmitted through to the second line

58

Goddard ECE329  
Lectures 27-30

## TL Discontinuity Looks Like Load Resistor with $R = Z_{02}$

The reflection coefficient for the two configurations are the same, but power is not dissipated in the first case, rather it is transmitted down the line.




$$\Gamma = \frac{Z_{02} - Z_{01}}{Z_{02} + Z_{01}}$$

$$\Gamma = \frac{Z_{02} - Z_{01}}{Z_{02} + Z_{01}}$$

59

Goddard ECE329  
Lectures 27-30

## Challenge Question: TL Discontinuity



- For a right moving wave (into the splitter), the fraction of power that is reflected is:  
(a) 1/9, (b) 1/4, (c) 1/3, (d) 1/2, (e) 2/3


Given your answer, what is the power transmitted down each line?

60

Goddard ECE329  
Lectures 27-30

LG's question

## Example



$\delta(t)$  is a unit impulse function.


First step: Calculate  $V^+$ ,  $I^+$ , and  $\Gamma$  at each location

Second step: Draw a bounce diagram to determine magnitude of pulses that come out the end of the third TL

61

Goddard ECE329  
Lectures 27-30

## Step 1: $V^+$ , $I^+$ , $\Gamma$




$$V^+ = V_0 \frac{Z_0}{R_g + Z_0} = 1 \delta \frac{50}{50 + 50} = 0.5 \delta V$$

$$I^+ = \frac{V^+}{Z_0} = \frac{0.5 \delta}{50} = 0.01 \delta A$$


62

Goddard ECE329  
Lectures 27-30




63

Goddard ECE329  
Lectures 27-30




64

Goddard ECE329  
Lectures 27-30









65

Goddard ECE329  
Lectures 27-30




66

Goddard ECE329  
Lectures 27-30



## Time Domain Reflectometry



Goddard ECE329  
 Lectures 27-30

73

Transmission line or device under test  
 $v_p = 10^8 \text{ m/s}$

$$Z_{01} = 50\Omega$$

$$T = T_0 = 1\text{ ns}$$

$$\tau_v = 3/2$$

$$\tau_r = 1/2$$

$$\Gamma = -1/2$$

$$\Gamma = 1/2$$

$$\Gamma = 0$$

$$\Gamma = ???$$

$$V' = 0.5$$


$$V' = 0.75$$

$$V = ???$$

$$V = -0.375$$

$$V' = ???$$
</

### (Optional) Inductive Termination




$$V^+ = \frac{V_0}{2}$$

$$I^+ = \frac{V^+}{Z_0} = \frac{V_0}{2Z_0}$$

79

Goddard ECE329  
Lectures 27-30

### (Optional) Inductive Termination



$$V^+ = \frac{V_0}{2}$$

$$I^- = -\frac{V^-(t)}{Z_0}$$

$$I^+ = \frac{V^+}{Z_0} = \frac{V_0}{2Z_0}$$

$$\text{For the inductor: } V = L \frac{dI}{dt}$$

80

Goddard ECE329  
Lectures 27-30

### (Optional) Two ways to solve

- Rigorous mathematical method
  - Laplace Transform
  - We will do this first
- Shortcut method

Goddard ECE329  
Lectures 27-30

81

### (Optional)

### Diff Eqn for the Inductor

$$V = L \frac{dI}{dt} \Rightarrow (V^+ + V^-(t)) = L \frac{d(I^+ + I^-(t))}{dt}$$

$$\frac{V_0}{2} + V^-(t) = L \frac{d}{dt} \left( \frac{V_0}{2Z_0} - \frac{V^-(t)}{Z_0} \right)$$

$$\frac{V_0}{2} = -\frac{L}{Z_0} \frac{dV^-(t)}{dt} - V^-(t)$$

$$\frac{dV^-(t)}{dt} + \frac{Z_0}{L} V^-(t) = -\frac{Z_0}{L} \frac{V_0}{2}$$

Laplace Transform  $V(t')$  to  $F(s)$

$t' = t - T$

$$s\hat{V}^-(s) - V^-(0) + \frac{Z_0}{L}\hat{V}^-(s) = -\frac{Z_0}{L} \frac{V_0}{2} \frac{1}{s}$$

82

Goddard ECE329  
Lectures 27-30

### (Optional) Laplace Transform for Inductor

Initial Condition At  $t=T$ , i.e.  $t'=0$ , inductor current = 0 since inductor "looks" like an OPEN CIRCUIT

$$I = I^+ + I^-(T) = 0 \Rightarrow \frac{V_0}{2Z_0} - \frac{V^-(0)}{Z_0} = 0 \Rightarrow V^-(0) = V_0/2$$

$$s\hat{V}^-(s) - \frac{V_0}{2} + \frac{Z_0}{L}\hat{V}^-(s) = -\frac{Z_0}{L} \frac{V_0}{2} \frac{1}{s} \Rightarrow \hat{V}^-(s) = \frac{sL - Z_0}{sL + Z_0} \frac{V_0}{2s}$$

In s-space, we have  $V(s) = \Gamma(s) V^+(s)$  with:

$$\Gamma(s) = \frac{Z(s) - Z_0}{Z(s) + Z_0}$$

$$\hat{V}^+(s) = \frac{V_0}{2s}$$

$$Z(s) = sL \text{ for an inductor}$$

83

Goddard ECE329  
Lectures 27-30


### (Optional)

### Invert Laplace Transform

$$\hat{V}(s) = \hat{V}^+ + \hat{V}^- = \frac{V_0}{2s} + \frac{V_0}{2s} \frac{sL - Z_0}{sL + Z_0} = \frac{V_0}{2s} \frac{2sL}{sL + Z_0} = \frac{V_0}{s + Z_0/L}$$

$$V(t) = V_0 e^{-(Z_0/L)t} = V_0 e^{-(Z_0/L)(t-T)} \quad t > T$$

$V(t)$  [volts]




84

Goddard ECE329  
Lectures 27-30

### (Optional) Shortcut Method

$$V(t) = V_0 e^{-(Z_0/L)(t-T)} \quad t > T$$





At  $t=T$  the inductor  
"looks" like an OPEN  
CIRCUIT

At  $t=\infty$  the inductor  
"looks" like a CLOSED CIRCUIT

85

Goddard ECE329  
Lectures 27-30


### (Optional) Shortcut Method



86

Goddard ECE329  
Lectures 27-30

### (Optional) Shortcut Method



At  $t=T$  the inductor  
"looks" like an open ckt

At  $t=\infty$  the inductor  
"looks" like a closed ckt


87

Goddard ECE329  
Lectures 27-30

### (Optional) Shortcut Method

V(t) [volts]

What happens "in between"?  
We know  $V(t)$  has exponential  
decay with time constant of  $L/Z_0$



88

Goddard ECE329  
Lectures 27-30

### (Optional) Summary of Shortcut Method


- Solve for voltage and current with inductive or reactive elements in their initial uncharged state
  - Inductor: Open
  - Capacitor: Short
- Solve for voltage and current with elements in their final charged state
  - Inductor: Short
  - Capacitor: Open
- Solve for circuit time constant for exponential function that occurs between initial and final states

89


Goddard ECE329  
Lectures 27-30

### (Optional) Shortcut Method

$$\tau = Z_{eq} C$$




$$\tau = \frac{L}{Z_{eq}}$$



90



Goddard ECE329  
Lectures 27-30

### (Optional) Shortcut Method Inductor Voltage / Capacitor Current



Goddard ECE329  
Lectures 27-30

### (Optional) Shortcut Method Inductor Current / Capacitor Voltage



Goddard ECE329  
Lectures 27-30

91 92


### (Optional) Shortcut Method Warning

- Only for reactive elements charged by DC source with no back reflections

93

Goddard ECE329  
Lectures 27-30

### (Optional) P6.21 (p430) – TDR example



No initial charge or current. Determine the unknown single element (R, L, or C) and the ratio  $Z_{02}/Z_{01}$

94

### (Optional) Calculation Space

95

Goddard ECE329  
Lectures 27-30

### (Optional) Lecture 30 Summary

- Reactive terminations and discontinuities require solving differential equations or studying start/end behavior & time constants

– Reflection coefficient  $\Gamma$  varies in time

$$\tau = Z_{eq} C$$

$$\tau = \frac{L}{Z_{eq}}$$

$$Z_{eq}$$

- Next class

– Chapter 7 (TL in frequency domain)

96

Goddard ECE329  
Lectures 27-30

## ECE 329 Lectures 31-34

Sections 7.A, 7.3, 7.1  
(Section 31-34 in Online Notes)

Line Terminated by an Arbitrary Load  
Smith Charts  
Short and Open Circuited TLs  
Half and Quarter Wave Transformers

Goddard ECE329  
Lectures 31-34

© 2008, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited


1

## Example

- Find  $\Gamma_L$  for a TL with  $Z_0=60\Omega$  that is terminated with an RLC series combo:  $R=30\Omega$ ,  $L=1\mu H$ ,  $C=100pF$  at the following radian frequencies (a)  $\omega=10^8$  and (b)  $\omega=2\times 10^8$
- Hint:  $Z_c=1/(j\omega C)$  and  $Z_L=j\omega L$

2

### TL's in Co-sinusoidal steady state



Distributed circuits are best handled with phasor and Fourier techniques and with Smith charts

$$f(t) = \operatorname{Re}[Fe^{j\omega t}]$$

$$V(z, t) = \operatorname{Re}[\tilde{V}(z)e^{j\omega t}]$$

$$I(z, t) = \operatorname{Re}[\tilde{I}(z)e^{j\omega t}]$$

3

Goddard ECE329  
Lectures 31-34

### Phasors satisfy usual TL equations

$$\left. \begin{aligned} \frac{\partial V}{\partial z} &= -\mathcal{L} \frac{\partial I}{\partial t} \\ \frac{\partial I}{\partial z} &= -\mathcal{C} \frac{\partial V}{\partial t} \end{aligned} \right\} \left. \begin{aligned} \frac{d\tilde{V}}{dz} &= -\mathcal{L}(j\omega \tilde{I}) \\ \frac{d\tilde{I}}{dz} &= -\mathcal{C}(j\omega \tilde{V}) \end{aligned} \right\} \left. \begin{aligned} \frac{d^2\tilde{V}}{dz^2} &= -\mathcal{L}\mathcal{C}\omega^2 \tilde{V} \\ \frac{d^2\tilde{I}}{dz^2} &= -\mathcal{L}\mathcal{C}\omega^2 \tilde{I} \end{aligned} \right.$$

$$\tilde{V} = V^+ e^{\mp j\beta z}$$

$$\tilde{I} = \pm \frac{V^\pm}{Z_0} e^{\mp j\beta z}$$

$$\beta = \omega \sqrt{\mathcal{L}\mathcal{C}}$$

$$Z_0 = \sqrt{\mathcal{L}/\mathcal{C}}$$

$$\tilde{V} = V^+ e^{j\beta d} + V^- e^{-j\beta d}$$

$$\tilde{I} = \frac{1}{Z_0} (V^+ e^{j\beta d} - V^- e^{-j\beta d})$$

4

Goddard ECE329  
Lectures 31-34

### Boundary Condition at Load

$$\Gamma_L = \frac{Z_L - Z_0}{Z_L + Z_0}$$

$$V^- = \Gamma_L V^+$$

$$\tilde{V}(d) = V^+ e^{j\beta d} + V^- e^{-j\beta d} = V^+ e^{j\beta d} (1 + \Gamma_L e^{-2j\beta d})$$

$$\tilde{I}(d) = \frac{1}{Z_0} (V^+ e^{j\beta d} - V^- e^{-j\beta d}) = \frac{V^+}{Z_0} e^{j\beta d} (1 - \Gamma_L e^{-2j\beta d})$$

5


Goddard ECE329  
Lectures 31-34

### Key Definition: Line Impedance

$$Z(d) \equiv \frac{\tilde{V}(d)}{\tilde{I}(d)}$$

$$Z(d) = Z_0 \frac{1 + \Gamma_L e^{-2j\beta d}}{1 - \Gamma_L e^{-2j\beta d}}$$

Equivalent Circuit



$$\tilde{V}(l) = \tilde{F} \frac{Z(l)}{Z(l) + Z_g} = V^+ (e^{j\beta l} + \Gamma_L e^{-j\beta l})$$

Allows you to solve for  $V^+$  and thus get  $V(d, t)$  and  $I(d, t)$

6

Goddard ECE329  
Lectures 31-34

## Challenge Question: Line Impedance

$$Z(d) = \frac{\tilde{V}(d)}{\tilde{I}(d)}$$

$$Z(d) = Z_0 \frac{1 + \Gamma_L e^{-2j\beta d}}{1 - \Gamma_L e^{-2j\beta d}}$$



- What is the smallest distance  $d$  from the load for which input impedance = load impedance?

- $d_{\min} = \lambda/8$
- $d_{\min} = \lambda/4$
- $d_{\min} = \lambda/3$
- $d_{\min} = \lambda/2$
- $d_{\min} = \lambda$

Goddard ECE329  
Lectures 31-34


LG's question

7

## Challenge Question: Line Impedance

$$Z(d) = \frac{\tilde{V}(d)}{\tilde{I}(d)}$$

$$Z(d) = Z_0 \frac{1 + \Gamma_L e^{-2j\beta d}}{1 - \Gamma_L e^{-2j\beta d}}$$



- What is the smallest distance  $d$  from the load for which input voltage = load voltage?

- $d_{\min} = \lambda/8$
- $d_{\min} = \lambda/4$
- $d_{\min} = \lambda/3$
- $d_{\min} = \lambda/2$
- $d_{\min} = \lambda$

Goddard ECE329  
Lectures 31-34

LG's question

8

## Key Definition: Generalized Reflection Coefficient

$$\Gamma(d) \equiv \frac{\tilde{V}^-(d)}{\tilde{V}^+(d)}$$

$$\Gamma(d) = \frac{V^- e^{-j\beta d}}{V^+ e^{j\beta d}} = \Gamma_L e^{-2j\beta d}$$

Allows you to find the backwards wave if forward wave is known

Goddard ECE329  
Lectures 31-34

9

## Key Definitions: Admittance and Normalized Impedance

Characteristic Admittance

$$Y_0 \equiv \frac{1}{Z_0}$$

Normalized Impedance

$$z(d) \equiv \frac{Z(d)}{Z_0}$$

$$z(d) = \frac{1 + \Gamma(d)}{1 - \Gamma(d)}$$

Normalized Admittance

$$y(d) \equiv \frac{1}{z(d)}$$

$$y(d) = \frac{1 - \Gamma(d)}{1 + \Gamma(d)}$$

$$\Gamma(d) = \Gamma_L e^{-2j\beta d}$$

10

Goddard ECE329  
Lectures 31-34

## Converting between Impedance and Reflection

$$\Gamma(d) = \Gamma_L e^{-2j\beta d}$$

$$z(d) = \frac{1 + \Gamma(d)}{1 - \Gamma(d)}$$

Invert to solve for  $\Gamma(d)$

$$\Gamma(d) = \frac{z(d) - 1}{z(d) + 1}$$

11

Goddard ECE329  
Lectures 31-34

## Smith Chart

$$\Gamma = \frac{z - 1}{z + 1}$$

$$z = r + jx$$


$$r \geq 0$$

$$\Gamma = \Gamma_r + j\Gamma_i$$

$$\Gamma_r = \frac{r^2 + x^2 - 1}{(r + 1)^2 + x^2}$$

$$\Gamma_i = \frac{2x}{(r + 1)^2 + x^2}$$

$$|\Gamma| \leq 1$$



PrintFreeGraphPaper.com  
© Analog Instruments Company  
Used with permission

12


## ECE 329 Lecture 32

### Short and Open Circuited Lines

Goddard ECE329  
Lectures 31-34

13

### Standing Waves for SC Line



$$\tilde{V}(d) = V^+ (e^{j\beta d} - e^{-j\beta d}) = 2jV^+ \sin(\beta d)$$

$$\tilde{I}(d) = \frac{V^+}{Z_0} (e^{j\beta d} + e^{-j\beta d}) = 2Y_0 V^+ \cos(\beta d)$$


$$Z(d) \equiv \frac{\tilde{V}(d)}{\tilde{I}(d)} = jZ_0 \tan \beta d$$

14

Goddard ECE329  
Lectures 31-34

### Standing Waves for SC Line

$$\begin{aligned} V(d, t) &= \operatorname{Re}[\tilde{V}(d)e^{j\omega t}] = \operatorname{Re}[2jV^+ \sin(\beta d)e^{j\omega t}] \\ &= \operatorname{Re}[2e^{j\pi/2} V^+ e^{j\theta} \sin(\beta d)e^{j\omega t}] \\ &= 2|V^+| \sin(\beta d) \operatorname{Re}[e^{j(\omega t + \theta + \pi/2)}] \\ &= 2|V^+| \sin(\beta d) \cos(\omega t + \theta + \pi/2) \\ &= -2|V^+| \sin(\beta d) \sin(\omega t + \theta) \end{aligned}$$



Goddard ECE329  
Lectures 31-34


15

### Standing Waves for SC Line

$$V(d, t) = -2|V^+| \sin(\beta d) \sin(\omega t + \theta)$$

$$I(d, t) = 2Y_0 |V^+| \cos(\beta d) \cos(\omega t + \theta)$$

$V(0, t) = 0$  always (voltage null)  
 $I(0, t)$  varies (current maxima)




Dependence is different than traveling wave:  $\omega t \pm \beta z$

16

Goddard ECE329  
Lectures 31-34

### Input Impedance for SC Line

$$Z_{in} = Z(l) = jZ_0 \tan \beta l = jZ_0 \tan \frac{2\pi l}{\lambda_p}$$



Is equivalent to:

17

Goddard ECE329  
Lectures 31-34

### SC Line can act as an inductor or a capacitor depending on $\beta l$



$$Z_{in} = jZ_0 \tan \beta l$$

If  $\tan(\beta l) > 0$ , shorted TL is inductive

If  $\tan(\beta l) < 0$ , shorted TL is capacitive

e.g.  $\beta l < \pi/2$   
or  $l < \lambda/4$ , TL is inductive

Goddard ECE329  
Lectures 31-34



18

Show that the equivalent inductance is  $L=\mathfrak{L}l$  if  $\lambda >> 4l$

$$Z_{in} = jZ_0 \tan \beta l$$

$$Z_L = j\omega L$$


19

Goddard ECE329  
Lectures 31-34

For  $l=$ even  $\lambda/4$ , TL is a short  
For  $l=$ odd  $\lambda/4$ , TL is an open

$$Z_{in} = jZ_0 \tan \beta l = \begin{cases} 0 = \text{a short for } \beta l = n\pi, n = 0, 1, 2, \dots \\ \infty = \text{an open for } \beta l = (n + 1/2)\pi \end{cases}$$

If  $Z_{in}=0$ , voltage drop is zero, just like a short  
If  $Z_{in}=\infty$ , current is zero, just like an open



20

Goddard ECE329  
Lectures 31-34

## Example


- A TL is shorted and your job is to find the location to fix it. You are equipped with a tunable frequency generator and an ammeter. Compare this to TDR.

21

Goddard ECE329  
Lectures 31-34

## Exercise


Locate  $z(0)$  and  $\Gamma'(0)$  of the shorted line on the S.C., and observe how  $z(d)$  and  $\Gamma'(d)$  vary as  $d$  increases, noting in particular to what happens at  $d = \lambda/4$  (open conditions are reached) and at  $d = \lambda/2$  (back to short conditions)



22

Goddard ECE329  
Lectures 31-34

## Standing Waves for OC Line



$$\tilde{V}(d) = V^+ (e^{j\beta d} + e^{-j\beta d}) = 2V^+ \cos(\beta d)$$

$$\tilde{I}(d) = \frac{V^+}{Z_0} (e^{j\beta d} - e^{-j\beta d}) = 2jY_0 V^+ \sin(\beta d)$$

$$Y(d) \equiv \frac{1}{Z(d)} = \frac{\tilde{I}(d)}{\tilde{V}(d)} = jY_0 \tan \beta d$$

23

Goddard ECE329  
Lectures 31-34


## Standing Waves for OC Line

Same phasor algebra as before with current & voltage reversed!

$$I(d, t) = -2Y_0 |V^+| \sin(\beta d) \sin(\omega t + \theta)$$

$$V(d, t) = 2|V^+| \cos(\beta d) \cos(\omega t + \theta)$$

$I(0, t) = 0$  always (current null)  
 $V(0, t)$  varies (voltage maxima)




24

Goddard ECE329  
Lectures 31-34

## Input Admittance for OC Line

$$Y_{in} = Y(l) = jY_0 \tan \beta l = jY_0 \tan \frac{2\pi l}{v_p}$$



25

Goddard ECE329  
Lectures 31-34


OC Line can act as an inductor or a capacitor depending on  $\beta l$

$$Y_{in} = jY_0 \tan \beta l$$

If  $\tan(\beta l) < 0$ , shorted TL is inductive

If  $\tan(\beta l) > 0$ , shorted TL is capacitive

e.g.  $\beta l < \pi/2$   
or  $l < \lambda/4$ , TL is capacitive



Equivalent Circuit:

26

Goddard ECE329  
Lectures 31-34

Show that the equivalent capacitance is  $C = \mathcal{C}_l$  if  $\lambda >> 4l$

$$Y_{in} = jY_0 \tan \beta l$$

$$Y_C = j\omega C$$


27

Goddard ECE329  
Lectures 31-34

For  $l = \text{even } \lambda/4$ , TL is an open  
For  $l = \text{odd } \lambda/4$ , TL is a short

$$Y_{in} = jY_0 \tan \beta l = \begin{cases} 0 = \text{an open for } \beta l = n\pi, n = 0, 1, 2, \dots \\ \infty = \text{a short for } \beta l = (n + 1/2)\pi \end{cases}$$

If  $Y_{in}=0$ , current is zero, just like an open  
If  $Y_{in}=\infty$ , voltage drop is zero, just like a short




28

Goddard ECE329  
Lectures 31-34

## Exercise

Locate  $z(0)$  and  $\Gamma'(0)$  of the shorted line on the O.C., and observe how  $z(d)$  and  $\Gamma'(d)$  vary as  $d$  increases, noting in particular to what happens at  $d = \lambda/4$  (short conditions are reached) and at  $d = \lambda/2$  (back to open conditions)



Goddard ECE329  
Lectures 31-34

PrintFreeGraphPaper.com  
© Analog Instruments Company  
Used with permission

$y(d)$  is  $z(d)$  shifted by  $\lambda/4$

- Proof:

$$\begin{aligned} z(d \pm \lambda/4) &= \frac{1 + \Gamma(d \pm \lambda/4)}{1 - \Gamma(d \pm \lambda/4)} = \frac{1 + \Gamma(d)e^{\pm 2j\beta\lambda/4}}{1 - \Gamma(d)e^{\pm 2j\beta\lambda/4}} & 2\beta\frac{\lambda}{4} = 2\frac{2\pi}{\lambda}\frac{\lambda}{4} = \pi \\ &= \frac{1 + \Gamma(d)e^{\pm j\pi}}{1 - \Gamma(d)e^{\pm j\pi}} = \frac{1 - \Gamma(d)}{1 + \Gamma(d)} = y(d) \end{aligned}$$

$$y(d) = z(d \pm \lambda/4)$$

Thus, the Smith Chart can be used for both  $z$  and  $y$

Opens and shorts exchange with each other every  $\lambda/4$

30

Goddard ECE329  
Lectures 31-34

## Lectures 31-32 Summary

- As  $d$  increases by  $\lambda/4$ , SC and OC TL switch from being a short ( $V=0$ ) to an open ( $I=0$ )
- Smith Chart is a bilinear transformation of the half plane  $z(d)$  ( $r \geq 0$ ) onto the unit circle  $|\Gamma| \leq 1$

$$\Gamma(d) = \frac{z(d)-1}{z(d)+1}$$

$$z(d) = \frac{1+\Gamma(d)}{1-\Gamma(d)}$$

### How to Use Smith Chart

- Calculate  $z(0)$  and find it on chart using  $r$  and  $x$
- Find  $\Gamma(0)$  as the distance and angle from origin
- Move CW along circle of radius  $|\Gamma(0)|$  to obtain  $\Gamma(d)$
- Read off  $z(d)$  by looking at grid location  $(r,x)$
- If needed, find  $y(d)$  on the same circle,  $180^\circ$  away

31

Goddard ECE329  
Lectures 31-34

## ECE 329 Lecture 33


### Microwave Resonators

32

Goddard ECE329  
Lectures 31-34

## Natural Resonances

- A lossless T.L. of any length  $l$  with open and/or short terminations on either ends can be considered a "microwave resonator"
  - It can sustain unforced voltage and current standing-wave oscillations at a set of discrete resonance frequencies  $\omega_n$
  - Example, for SC TL,  $z_{in}=\infty$  (open) or 0 (short) has standing waves for the set of  $\lambda_n$  satisfying  $l=n\lambda_n/4$



33


Goddard ECE329  
Lectures 31-34

## Parallel & Series Resonances

- We can find  $\lambda_n$  and  $\omega_n$  by applying the appropriate BCs at both ends

### Series resonance if $z_{in}(l)=0$


- Analogous to an LC circuit in series and requires a short placed across TL at  $d=l$
- Like a short input



34


### Parallel resonance: $y_{in}(l)=0$

- Analogous to an LC circuit in parallel and requires an open across the TL at  $d=l$
- Like an open input



Goddard ECE329  
Lectures 31-34

## Parallel & Series Resonances 4 simple cases



35

Goddard ECE329  
Lectures 31-34

## Examples

- a) Find the 3 lowest frequencies for parallel resonances if the load is shorted and  $v=c$ ,  $l=3m$ .

- b) Find the resonance frequencies for a 10m long TL that is open circuited at both ends if  $v = 2/3 c$ .

36

Goddard ECE329  
Lectures 31-34

## ECE 329 Lecture 34


### Half-wave and quarter-wave transformers

Goddard ECE329  
Lectures 31-34

37

### Half-wave transformers

- Given a fixed drive frequency  $\omega$ , there is a length of line  $l = \lambda/2$  such that:




- Note: Current and voltage both invert their algebraic signs

Goddard ECE329  
Lectures 31-34

38

### Half-wave transformers



- Proof:

$$e^{\pm j\beta l/2} = e^{\pm j\pi} = -1$$

$$\tilde{V}(d) = V^+ e^{j\beta d} + V^- e^{-j\beta d}$$


$$\therefore \tilde{V}_{in} = \tilde{V}(\lambda/2) = -V^+ - V^- = -\tilde{V}(0) = -\tilde{V}_L$$

$$\tilde{I}_{in} = \frac{V^+ e^{j\beta d} - V^- e^{-j\beta d}}{Z_0} = \frac{-V^+ + V^-}{Z_0} = -\tilde{I}_L$$

Goddard ECE329  
Lectures 31-34

39

### Challenge Question: Half-wave transformers



- What is the input impedance of a half-wave transformer?

- $Z_{in} = Z_0$
- $Z_{in} = Z_0 + Z_L$
- $Z_{in} = 1/(1/Z_0 + 1/Z_L)$
- $Z_{in} = Z_L$
- $Z_{in} = Z_0^2/Z_L$


Goddard ECE329  
Lectures 31-34

LG's question

40

### Quarter-wave transformers

- Given a fixed drive frequency  $\omega$ , there is a length of line  $l = \lambda/4$  such that:




- Note: The current through the load does not depend on  $Z_L$  (current-forcing)

Goddard ECE329  
Lectures 31-34

41

### Quarter-wave transformers



- Proof:

$$e^{\pm j\beta l/4} = e^{\pm j\pi/2} = \pm j$$

$$\tilde{V}(d) = V^+ e^{j\beta d} + V^- e^{-j\beta d}$$


$$\tilde{V}_{in} = jV^+ - jV^- = j\tilde{I}_L Z_0 \Rightarrow \tilde{I}_L = -j\tilde{V}_{in}/Z_0$$

$$\tilde{I}_{in} = \frac{jV^+ - (-jV^-)}{Z_0} = j\frac{\tilde{V}_L}{Z_0} \Rightarrow \tilde{V}_L = -j\tilde{I}_{in} Z_0$$

Goddard ECE329  
Lectures 31-34

42

## Challenge Question: Quarter-wave transformers



- What is the input impedance of a quarter-wave transformer?


- $Z_{in} = Z_0$
- $Z_{in} = Z_0 + Z_L$
- $Z_{in} = 1/(1/Z_0 + 1/Z_L)$
- $Z_{in} = Z_L$
- $Z_{in} = Z_0^2/Z_L$

43

Goddard ECE329  
Lectures 31-34

LG's question

## Verifying an Identity




- Verify the Lecture 32 result:  $y(d) = z(d \pm \lambda/4)$

44

Goddard ECE329  
Lectures 31-34

## Half-wave transformer as 2 quarter-wave transformer



45

Goddard ECE329  
Lectures 31-34

## Examples

- For  $Z_L = 50 + 50j\Omega$ , find  $Z_{in}$  for a  $\lambda/4$  transformer with  $Z_0 = 50\Omega$ .
- Check your answer with a Smith Chart.
- Find  $V_{in}$  if a source with open circuit voltage  $V_g = 100V$  and Thevenin impedance  $Z_g = j25\Omega$  is connected
- Find  $I_L$  and  $\langle P_L \rangle$ .

46

Goddard ECE329  
Lectures 31-34

## Examples

- For  $Z_L = 100\Omega$ , find  $Z_{in}$  for a  $3\lambda/4$  TL if  $Z_0 = 50\Omega$ .
- Check your answer with a Smith Chart.
- Find  $V_L$  and  $I_L$  if a source with open circuit voltage  $V_g = j10V$  and Thevenin impedance  $Z_g = 25\Omega$  is connected.

47

Goddard ECE329  
Lectures 31-34

## Lecture 34 Summary

- TL transformers can be used to change the load impedance  $Z_L$  to a new value as seen at the input port  $Z_{in}$  and thus adjust  $V_L$  and  $I_L$
- If the TL is  $\lambda/4$ , then we have current forcing:

$$\tilde{I}_L = -j\tilde{V}_{in} / Z_0 \quad Z_L Z_{in} = Z_0^2$$

$$\tilde{V}_L = -j\tilde{I}_{in} Z_0$$

- If the TL is  $\lambda/2$ , then I and V both change their own signs:

$$\tilde{I}_L = -\tilde{I}_{in} \quad Z_L = Z_{in}$$

$$\tilde{V}_L = -\tilde{V}_{in}$$

48

Goddard ECE329  
Lectures 31-34

# ECE 329

## Lectures 35-36

### Rao - Sections 7.2, 7.3

### Online Notes – 35-36

#### Line Terminated by an Arbitrary Load


#### Standing Wave Parameters

#### Smith Charts

Goddard ECE329  
Lectures 35-36

© 2008, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

#### TL's in Co-sinusoidal steady state



Imposed condition on load  
end will result in some form  
of standing wave oscillation

$$f(t) = \operatorname{Re}[\tilde{F} e^{j\omega t}]$$

$$V(z, t) = \operatorname{Re}[\tilde{V}(z) e^{j\omega t}]$$

$$I(z, t) = \operatorname{Re}[\tilde{I}(z) e^{j\omega t}]$$

2

Goddard ECE329  
Lectures 35-36

#### Summary of Equations

$$\Gamma_L = \frac{Z_L - Z_0}{Z_L + Z_0}$$

$$V^- = \Gamma_L V^+$$

$$\Gamma(d) = \Gamma_L e^{-2j\beta d}$$

$$\tilde{V}(d) = V^+ e^{j\beta d} (1 + \Gamma_L e^{-2j\beta d}) = V^+ e^{j\beta d} (1 + \Gamma(d))$$

$$\tilde{I}(d) = \frac{V^+ e^{j\beta d}}{Z_0} (1 - \Gamma_L e^{-2j\beta d}) = \frac{V^+ e^{j\beta d}}{Z_0} (1 - \Gamma(d))$$

$$Z(d) \equiv \frac{\tilde{V}(d)}{\tilde{I}(d)} = Z_0 \frac{1 + \Gamma(d)}{1 - \Gamma(d)}$$

$$z(d) = \frac{1 + \Gamma(d)}{1 - \Gamma(d)}$$

$$\Gamma(d) = \frac{z(d) - 1}{z(d) + 1}$$

3


Goddard ECE329  
Lectures 35-36

#### Standing Wave Parameters

Amplitude of the standing waves:

$$|\tilde{V}(d)| = |V^+| \|1 + \Gamma(d)\|$$

$$|\tilde{I}(d)| = Y_0 |V^+| \|1 - \Gamma(d)\|$$



Where would V\_min be?  
What about I\_min and I\_max?


4

Goddard ECE329  
Lectures 35-36

#### Standing Wave Parameters

$$|\tilde{V}(d)| = |V^+| \|1 + \Gamma(d)\|$$

$$|\tilde{I}(d)| = Y_0 |V^+| \|1 - \Gamma(d)\|$$



Unlike SC or OC where  $|\Gamma|=1$ ,  
now we have imperfect nulls for  
voltage and current b/c  $|\Gamma|<1$


Goddard ECE329  
Lectures 35-36

5

#### Standing Wave Parameters

$$\Gamma = 0.75e^{j\pi/4}$$

$$\text{VSWR} = \frac{V_{\max}}{V_{\min}} = 7$$




Peak positions move  
in time since it is a  
standing wave plus a  
traveling wave

Goddard ECE329  
Lectures 35-36

$$\Gamma = 1.0e^{j\pi/4}$$

$$\text{VSWR} = \frac{V_{\max}}{V_{\min}} = \infty$$




Peak positions stay  
constant since it is  
purely a standing  
wave

Goddard ECE329  
Lectures 35-36

1

## Challenge Question: VSWR



- If  $Z_L = Z_0 = 50\Omega$  and  $Z_g = 100\Omega$ , what will be the VSWR?

- $\infty$
- 2
- 1
- $1/2$
- 0

Goddard ECE329  
Lectures 35-36


LG's question

7

## Standing Wave Useful Facts

$$VSWR = \frac{V_{\max}}{V_{\min}} = \frac{1+|\Gamma|}{1-|\Gamma|} = z(d_{\max})$$

Thus,



$$VSWR = z(d_{\max}) = y(d_{\min})$$


because

$$y(d) = z(d \pm \lambda/4)$$

8

## Lecture 35 Summary

- As  $d$  increases, amplitude  $|V(d)|$  varies like  $|1+\Gamma|$  while  $|I(d)|$  varies like  $|1-\Gamma|$



- $VSWR = V_{\max}/V_{\min} = z(d_{\max})$

Goddard ECE329  
Lectures 35-36

## ECE 329 Lecture 36 Sections 7.2

More Standing Wave Parameters and  
More Practice with Smith Charts

Goddard ECE329  
Lectures 35-36

## Example: VSWR measurements

- Find  $Z_L$  if VSWR measurements are made on a line with  $Z_0=60\Omega$ :
- $SWR = 1.5$  and  $d_{\min} = 0$
  - $SWR = 3.0$  and  $d_{\min} = 3$  and  $9\text{ cm}$
  - $SWR = 2.0$  and  $d_{\min} = 3$  and  $7\text{ cm}$

Goddard ECE329  
Lectures 35-36

From D7.5 (p 463) of old book

11

## Calculation Space

Goddard ECE329  
Lectures 35-36

12

## Example: Input Impedance

- Find  $Z_{in}$  if  $Z_L = 45 + 60j\Omega$  and  $Z_0 = 75\Omega$  and  $v_p = c$  for the following cases:

(a)  $f = 15\text{MHz}$ ,  $l = 5\text{m}$

(b)  $f = 50\text{MHz}$ ,  $l = 3\text{m}$

(c)  $f = 37.5\text{MHz}$ ,  $l = 5\text{m}$

13

Goddard ECE329  
Lectures 35-36


From D7.6 (p 463) of old book

## Calculation Space

14

Goddard ECE329  
Lectures 35-36

## Example



- Using SC, determine: (a)  $z(0)$ , (b)  $\Gamma(0)$ , (c) VSWR, (d) locations of  $V_{max}$

15


Goddard ECE329  
Lectures 35-36

## Calculation Space

16

Goddard ECE329  
Lectures 35-36

## Example



- Continue the problem and using SC, determine: (e)  $\Gamma(l)$ , (f)  $Z_{in}$ , (g)  $V(l)$ , (h)  $I(l)$ , (i)  $\langle P \rangle$

17

Goddard ECE329  
Lectures 35-36

## Calculation Space

18

Goddard ECE329  
Lectures 35-36

# ECE 329

## Lectures 37-39

### Sections 7.3

### Online Notes: 37-39

Average Power  
 Quarter Wave Transformer Matching  
 Single Stub Matching  
 (Optional) Double Stub Matching  
 Distribution Networks  
 Lossy Line

Goddard ECE329  
 Lectures 37-39

© 2008, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

## Average Power

- In a lossless TL circuit,

$$\langle P_{in} \rangle = \langle P(d) \rangle = \langle P_L \rangle$$

Note that  $\langle P(d) \rangle = \frac{1}{2} \operatorname{Re}[\tilde{V}(d)\tilde{I}^*(d)]$

$$\text{Hint: } \operatorname{Re}[z-z^*]=0 \\ = \dots = \frac{1}{2} \left( \frac{|V^+|^2}{Z_0} - \frac{|V^-|^2}{Z_0} \right) = \frac{1}{2} \frac{|V^+|^2}{Z_0} (1 - |\Gamma_L|^2)$$

and so  $|\Gamma_L|^2$  represents the power reflection coefficient

2

Goddard ECE329  
 Lectures 37-39


## Impedance matching

- When  $Z_L \neq Z_0$ , power is reflected back to the generator and  $VSWR > 1$  (bad)
- Impedance matching achieves  $VSWR=1$  by adjusting the input impedance,  $Z_{in}$ , to be equal to the TL characteristic impedance,  $Z_0$

3


Goddard ECE329  
 Lectures 37-39

## Quarter Wave Matching Transformer



4

## Quarter Wave Matching Transformer




### Key Observations:

- $Z_0$  and  $Z_q$  are real since TL's are lossless
- $Z_1 = Z_0$  for a match so  $Z_1$  must be real
- $Z_1 Z_2 = Z_0^2$  since we have a QW transformer
- $Z_2$  must be real from equation #3
- $d_q$  must be at a voltage max or min from #4

5

Goddard ECE329  
 Lectures 37-39

## Quarter Wave Matching Transformer



$$\text{Solution: } Z_q = \sqrt{Z_0 Z_2} = Z_0 \sqrt{z_2}$$

$$d_q = \begin{cases} d_{\max} = \frac{\lambda \theta}{4\pi} \\ d_{\min} = \frac{\lambda \theta}{4\pi} + \frac{\lambda}{4} \bmod \lambda/2 \end{cases}$$

$\theta = \operatorname{angle}(\Gamma_L)$

6


Goddard ECE329  
 Lectures 37-39

### Example: Design a QWT (2 choices)

$Z_0=50\Omega$ ; load is  $R=30\Omega$  in series with  $L=1nH$  for  $\lambda=10mm, V_p=c/\pi$

Hints:  
Find  $z(0)$   
Get  $|\Gamma_L|$  &  $\theta$   
Find  $d_{\max}$ ,  $d_{\min}$   
Get both  $Z_2$ 's

Goddard ECE329  
Lectures 37-39




7

### Similar to Optics

- Anti-reflection coatings:

- thickness =  $\lambda/4$  and  $n_q = \sqrt{n_1 n_2}$




Anti-reflection coatings work by producing two reflections which interfere destructively with each other.



<http://hyperphysics.phy-astr.gsu.edu/Hbase/phyopt/antiref.html> 8

Goddard ECE329  
Lectures 37-39

### Challenge Question: QWT matching



- For QWT matching, which is **false**:
- (a)  $VSWR=1$  in segment 1
- (b) segment 1 can have any length
- (c) there is a voltage min or max at both the left and right edges of segment 2
- (d)  $\Gamma(d)=1$  in segment 3
- (e)  $d_q$  can be increased by integer multiples of  $\lambda/2$  without affecting the matching


9

Goddard ECE329  
Lectures 37-39

LG's question

### Single Stub Matching

#### Before:



After inserting a shorted stub in parallel,  $y_{in}=1$  so no more reflections and  $VSWR=1$

More convenient than QWT since stub has same impedance




$\tilde{Z}_L$

10

Adjust  $d_s$  and  $y_s$  for match

Goddard ECE329  
Lectures 37-39

### Single Stub Matching




Key Observations:

- $y_{in}=1$  for a match because  $Z_{in}=Z_0 \rightarrow y_{in}=Z_0/Z_{in}=1$
- $y_{in}=y_1'+y_s$  since admittance adds for parallel elements
- $y_s=1/(j \tan \beta s)=jb$  is purely imaginary for SC line
  - See Lect 32, slide 18:  $Z_{in}=jZ_0 \tan(\beta s)$
  - Needed amount of susceptance, b, depends on  $|\Gamma_L|_{11}$

Goddard ECE329  
Lectures 37-39

### (Optional) Single Stub Matching









$$y_1' = y_{in} - y_s = 1 - jb$$







$$\Gamma_1' = \frac{1 - y_1'}{1 + y_1'} = \frac{jb}{2 - jb} = \Gamma_L e^{-2j\beta s} \Rightarrow |\Gamma_L| = \frac{|b|}{\sqrt{4 + b^2}}$$

$$\therefore b = \pm \frac{2 |\Gamma_L|}{\sqrt{1 - |\Gamma_L|^2}}$$

12

Goddard ECE329  
Lectures 37-39





**ECE Illinois** DEPARTMENT OF ELECTRICAL AND COMPUTER ENGINEERING  
UNIVERSITY OF ILLINOIS AT URBANA-CHAMPAIGN

"New" Course: ECE 446 for Fall 2017  
Principles of Experimental Research

Principles of experimental research is an inter-disciplinary course designed for graduate students in electrical engineering. The course will teach ECE students how to plan and execute any experiment. An experiment is defined as a process to determine the effect of one or more independent variables on some dependent variable. The course will cover: (1) design of experiments, (2) planning and execution of experiments, (3) analysis of data, and (4) presentation of results. The course will also introduce statistical methods for hypothesis testing, and the use of computers for data analysis and interpretation.

Prof. Goddard TA: 11:11-11:50AM in ECEB 4070  
4 Credit Hours for Grad and Undergrad Students  
(An ECE Lab Elective or MEng Professional Development Course)

Goddard ECE329  
Lectures 37-39

25

(Optional)

## ECE 329 Lecture 38(b)

### Double Stub Matching

26

**(Optional)**  
**Double Stub Matching**

**Before:**  
A graph shows V'/(1+|Γ|) vs d in units of λ/4. The curve starts at 1.0, dips to 0.5 at d=0, rises to 1.5 at d=λ/4, and returns to 1.0 at d=λ/2. A formula for VSWR is given:  $V_{\text{SWR}} = \frac{V_{\text{min}}}{V_{\text{max}}} = \frac{1+|\Gamma|}{1-|\Gamma|}$ .

After inserting two shorted stubs in parallel,  $y_{in} = 1$  so no more reflections and VSWR=1

More convenient than SSM since stub locations are fixed

Adjust  $l_1$  and  $l_2$  for match

Goddard ECE329  
Lectures 37-39

27

**(Optional)**  
**Double Stub Matching**

- Derivation proceeds similar to SSM, but algebra gets complicated quickly (p468)

$$y_2 = y_{in} - y_{s2} = 1 - jb_2$$

$$\Gamma_2 = \frac{1 - y_2}{1 + y_2} = \frac{jb_2}{2 - jb_2} = \Gamma_1 e^{-2j\beta l_{12}} \Rightarrow \Gamma_1 = \frac{jb_2}{2 - jb_2} e^{2j\beta l_{12}}$$

$$y_1 = \frac{1 - \Gamma_1}{1 + \Gamma_1} \quad \text{Plug in } \Gamma_1 \text{ from above}$$

$$y_1 = y_1 - y_{s1} = y_1 - jb_1 \quad \text{Plug in } y_1 \text{ from above}$$

$y_1$  is known: start with  $y(0)$  and move CW by  $d_1$  (predetermined); so just have to solve for  $b_1$  and  $b_2$  satisfying the real/imaginary parts of  $y_1 = y_1 - jb_1$

28

**(Optional)**  
**Double Stub Matching**

- $y_1$  depends on  $b_2$  and not  $b_1$  so can solve for  $b_2$  from real part of  $y_1 = y_1 - jb_1$

$g' \equiv \text{Re}[y_1] = \text{Re}[y_1] = \text{function of } b_2$

$$b_2 = \frac{\cos \beta d_{12} \pm \sqrt{1/g' - \sin^2 \beta d_{12}}}{\sin \beta d_{12}}$$

Note that there will be no solution if  $g' > 1/\sin^2 \beta d_{12}$

Goddard ECE329  
Lectures 37-39

29

**(Optional)**  
**Double Stub Matching**

- With  $b_2$  solved, can find  $b_1$  from the imaginary part of  $y_1 = y_1 - jb_1$

$$b' \equiv \text{Im}[y_1] = \text{Im}[y_1] - b_1 \Rightarrow$$

$$b_1 = \text{Im}[y_1] - b' = \text{function of } b_2$$

$$b_1 = \frac{b_2^2 \sin 2\beta d_{12} - 2b_2 \cos 2\beta d_{12}}{2 - 2b_2 \sin 2\beta d_{12} + 2b_2^2 \sin^2 \beta d_{12}} - b'$$

Finally, given  $b_1$  and  $b_2$ , we can find  $l_1$  and  $l_2$  using:

$$l_s = \frac{\lambda}{2\pi} \tan^{-1} \left( -\frac{1}{b} \right) \bmod \lambda/2$$

30

Goddard ECE329  
Lectures 37-39


### (Optional) Example: Design DSM

- $Z_0=50\Omega$ , Termination is  $Z=30-40j\Omega$  and we choose to fix  $d_1=0$  and  $d_{12}=0.375\lambda$

31

Goddard ECE329  
Lectures 37-39

### (Optional) Double Stub Matching w/ S.C.



Key Observations:

- For a match,  $y_1'$  must be on unit conductance circle
- Thus,  $y_1$  is on the auxiliary circle
  - Auxiliary circle is UCC pivoted CCW towards the load by  $d_{12}$

32

Goddard ECE329  
Lectures 37-39

### Unit Conductance (Optional) Circle: $y_2'=1-jb_2$

Auxiliary Circle  $y_1$  is UCC pivoted  $d_{12}$  CCW towards load

Goddard ECE329  
Lectures 37-39

$d_{12}=0.375\lambda$

33

Repeat DSM:  $d_1=0$  (Optional)  
 $d_{12}=0.375\lambda$   
 $z(0)=0.6-0.8j$

To get  $y_1'$  on UCC, need  $y_1$  on AUX so draw AUX first using given  $d_{12}$

Goddard ECE329  
Lectures 37-39

34

Repeat DSM:  $d_1=0$  (Optional)  
 $d_{12}=0.375\lambda$   
 $z(0)=0.6-0.8j$

$$y(0)=0.6+0.8j$$

Since  $d_1=0$ ,  
 $y_1'=y(0)$

Goddard ECE329  
Lectures 37-39

$$y(0)=y_1$$

$$z(0)$$

35

Find susceptance to go from  $y_1$  along constant conductance circle to  $y_1$  on AUX

$$b_1=-0.89 \text{ or } b_1=2.72$$

$$l_1 = \frac{\lambda}{2\pi} \tan^{-1} \left( -\frac{1}{b} \right)$$

$$l_1=0.134\lambda \text{ or } l_1=0.056\lambda$$

Goddard ECE329  
Lectures 37-39

36

(Optional)

$y(0)=y_1$

$y_1$

$z(0)$

$y_1'$

$y_2'$

$y_2$

$y_1$

$y_1'$

$z(0)$

$y_1$

$y_1'$

$y_2$







$y_2'$

$y(0)$

$y_1$

$y_1'$

</





## 50Ω and 75Ω coax are so popular because ...

- The shunt conductance of the imperfect dielectric is small compared to the series resistance of the conductor, so:

$$\alpha \approx \frac{1}{2} \left( \frac{\mathcal{R}}{Z_0} + GZ_0 \right) \approx \frac{1}{2} \frac{\mathcal{R}}{Z_0}$$

Plugging in the formula for  $\mathcal{R}$  and  $Z_0$  of a coax with inner and outer radii  $a$  and  $b$ , you can show  $\alpha$  is minimized when  $b/a = 3.59$  (for fixed  $b$ ), which works out to 50Ω and 75Ω for a dielectric and air filled coax, respectively. Loss decreases with  $b$ , so use thicker coax to reduce loss.

49

Goddard ECE329  
Lectures 37-39

## Suggested courses that build on ECE329

|         |                                     | Other Pre-Reqs |
|---------|-------------------------------------|----------------|
| ECE 350 | Fields and Waves II                 |                |
| ECE 446 | Principles of Experimental Research | 313            |
| ECE 451 | Advanced Microwave Measurements     | 350            |
| ECE 452 | Electromagnetic Fields              | 350            |
| ECE 454 | Antennas                            | 350            |
| ECE 455 | Optical Electronics                 | 350            |
| ECE 453 | Wireless Communication Systems      | 342            |
| ECE 460 | Optical Imaging                     | 313            |

Goddard ECE329  
Lectures 37-39

"New" Course ECE 446 for Fall 2017  
Principles of Experimental Research

Then there is a  
lot more!!!  
ECE 446  
Prof. Goddard • M-F 11:15:00 AM in ECEB 4070  
4 Credit Hours for Graduate and Undergrad Students  
(An ECE Lab Elective or MEng Professional Development Course)

50

Good luck on the final!

- It was a pleasure teaching ECE329 this semester  
–Thank you for studying so hard ☺

51

Goddard ECE329  
Lectures 37-39

# ECE 329

## Review for Final Exam

(page and chapter #'s are for the old book)


Goddard ECE329  
Cumulative Review

© 2007, Lynford Goddard - Copying, publishing or distributing without express written permission is prohibited

Chapter 1

### Coulomb's Law Electric Field Around a Point Charge

$$\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_R$$



Field strength is proportional to the density of field lines

2

\* Important

### Calculating the Electric Field

Point Charge at position  $(x_1, y_1, z_1)$

Position where we want to calculate electric field at Position  $(x_2, y_2, z_2)$

$$\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_R$$

$$R = \sqrt{(x_2 - x_1)^2 + (y_2 - y_1)^2 + (z_2 - z_1)^2}$$


$$\hat{a}_R = \frac{(x_2 - x_1)\hat{a}_x + (y_2 - y_1)\hat{a}_y + (z_2 - z_1)\hat{a}_z}{R}$$

Unit vector pointing along direction from Q to Point

3

Goddard ECE329  
Cumulative Review

### Superposition of Fields



4

\* Important


### Patented 5-Step Program for Problem Solving

1. MAKE A **LARGE CLEAR DRAWING**
  - a. Also draw cross-sections if the problem is in 3D
  - b. Pick a coordinate system that is appropriate for the symmetry of the problem
2. Divide charge distributions into tiny pieces
3. Find  $dE$  of one tiny piece
4. Use SYMMETRY to eliminate any components that cancel (i.e. add to ZERO)
5. INTEGRATE to add contribution of ALL the tiny pieces

5

Goddard ECE329  
Cumulative Review

### Example: $F$ due to line of charge (1)



What is the small amount of force,  $dF$ , applied by a small sliver of the rod?

Differential charge in one small sliver (coul)


$$dF = \frac{\left[ \frac{Q}{L} dx \right]}{4\pi\epsilon_0 x^2} q \hat{a}_x$$

Differential force applied to q

6

Goddard ECE329  
Cumulative Review

## Ampere's Force Law



Force on current 1 due to current 2

Goddard ECE329  
Cumulative Review

7

## Lorentz Force Equation

If a region of space contains BOTH an **E** field and a **B** field, a moving charge will experience force from both at the same time...

$$\vec{F}_{TOTAL} = \vec{F}_E + \vec{F}_M$$

$$\vec{F}_{TOTAL} = q\vec{E} + q\vec{v} \times \vec{B}$$

8

Goddard ECE329  
Cumulative Review


## Application: Mass Spectrometers

### Part I: Velocity Selector

- Particles with a specific velocity in crossed EM fields are undeflected

$$\begin{aligned}\vec{E} &= E_0 \hat{a}_z \\ \vec{B} &= -B_0 \hat{a}_y \\ \vec{v} &= v_0 \hat{a}_x \\ \vec{F}_{TOTAL} &= q(E_0 - v_0 B_0) \hat{a}_z = 0 \text{ iff } v_0 = E_0 / B_0\end{aligned}$$

Goddard ECE329  
Cumulative Review



9

Chapter 2

## Surface Integrals

- Flux = # of arrows that pass thru a surface; it depends on:

- The density of vectors



- The angle of the surface



- The area of the surface




$$Flux = \vec{B} \bullet d\vec{S}$$

10

Goddard ECE329  
Cumulative Review

## "Closed" Bug Catching Net

Bug Density Vectors  
(Bugs/m<sup>2</sup>)



Goddard ECE329  
Cumulative Review

11

\* Important

## Gauss' Law for B Fields

Net flux of magnetic field lines through any closed surface MUST be zero.

$$\iint_S \vec{B} \bullet d\vec{S} = 0$$


12

Goddard ECE329  
Cumulative Review

\* Important

## Gauss' Law for E-fields

- Field lines begin on + charges, end on - ones
  - Electric flux out = Net charge enclosed, regardless of shape or location of charges



$$\psi_E = \iint_S \vec{D} \cdot d\vec{S} = Q_{\text{enclosed}}$$

FLUX OUT = CHARGE ENCLOSED

13

Goddard ECE329  
Cumulative Review

## Simple Example 1

6-sided cube with Q at the center:



Flux out of entire box = Q  
Flux out of one side = Q/6

6-sided cube with Q NOT at the center:




Flux out of entire box = Q  
Flux out of one side = ???

14

Goddard ECE329  
Cumulative Review

## Tricky Examples

Flux out of hemisphere with Q at the center = Q/2




15

Goddard ECE329  
Cumulative Review

\* Important

## Faraday's Law




- The EMF generated in the loop is the NEGATIVE of the rate of change of the magnetic flux enclosed in the loop
- Right Hand curls around C so thumb points in direction of dS

16

Goddard ECE329  
Cumulative Review

## Induced emf around rectangular loop in a time-varying B field




17

Goddard ECE329  
Cumulative Review

\* Important

## Ampere's Law



$$\int_C \vec{H} \cdot d\vec{l} = \iint_S \vec{J} \cdot d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \cdot d\vec{S}$$


MMF (Amps) = "Regular" Current (Amps) + Displacement Current (Amps)

18

Goddard ECE329  
Cumulative Review

## Displacement Current

- Current flow changes the amount of charge
  - Since the charge changes, the electric flux out of the surface changes, i.e. a displacement current



$$\vec{E} = \frac{Q}{4\pi\epsilon_0 R^2} \hat{a}_R$$

$$\psi_E = \iint_S \epsilon_0 \vec{E} \cdot d\vec{S} = \epsilon_0 E (\text{Surf Area})$$

$$= \epsilon_0 \frac{Q}{4\pi\epsilon_0 R^2} (4\pi R^2) = Q_{\text{enclosed}}$$


$$I_d = \frac{d\psi_E}{dt} = \frac{dQ_{\text{enclosed}}}{dt}$$

$$I_d = \frac{dQ_{\text{enclosed}}}{dt} = I_{\text{in}} \text{ because current in} = \text{current out}$$

19

Goddard ECE329  
Cumulative Review

## B for an infinitely long solid cylindrical conductor



No changing D-field so  
Ampere's Law, with  $d\psi_E/dt=0$ :

$$\oint_C \vec{H} \cdot d\vec{l} = I_{\text{enclosed}} = \iint_S \vec{J} \cdot d\vec{S}$$

$$2\pi H_\phi = \frac{I}{\pi a^2} \pi r^2 \text{ inside or } = I \text{ outside}$$


20

Goddard ECE329  
Cumulative Review

\* Important

## Conservation of Charge

In general, we can pour charges in from more than one direction, or take some out from other parts of the container



Net Rate of Current flow OUT = Net Rate of Charge DECREASE


$$\iint_S \vec{J} \cdot d\vec{S} = -\frac{dQ_{\text{enc}}}{dt} = -\frac{d}{dt} \iiint_V \rho dV$$

21


Goddard ECE329  
Cumulative Review

## Chapter 3


## Curl measures circulation



No rotation!



Anti-clockwise rotation.




Clockwise rotation.


22

Goddard ECE329  
Cumulative Review


## Divergence measures # of field lines created



Flux in = flux out  
so no sources or sinks inside V.



Flux out > flux in  
Positive divergence.  
Must be a source  
inside V.





Flux out < flux in  
Negative divergence.  
Must be a sink or drain inside V.


23

Goddard ECE329  
Cumulative Review

## Curl and Divergence



$\frac{dE_x}{dx} \neq 0$   
YES DIVERGENCE  
NO CURL  
Varies ALONG



$\frac{dE_y}{dx} \neq 0$   
NO DIVERGENCE  
YES CURL  
Varies ACROSS

24

Goddard ECE329  
Cumulative Review

## Curl and Divergence

$\iint_S (\nabla \times \vec{v}) \cdot d\vec{S} = \oint_C \vec{v} \cdot d\vec{l}$

Stokes' Theorem

$\iiint_V \nabla \cdot \vec{v} dV = \iint_S \vec{v} \cdot d\vec{S}$

Divergence Theorem

Goddard ECE329  
Cumulative Review

25

\*\*\* Extremely Important

## Maxwell's Equations

|                |   |   |
|----------------|---|---|
| Faraday's Law  | $\oint_C \vec{E} \cdot d\vec{l} = -\frac{d}{dt} \iint_S \vec{B} \cdot d\vec{S}$                                 | $\nabla \times \vec{E} = -\frac{d\vec{B}}{dt}$          |
| Ampere's Law   | $\oint_C \vec{H} \cdot d\vec{l} = \iint_S \vec{J} \cdot d\vec{S} + \frac{d}{dt} \iint_S \vec{D} \cdot d\vec{S}$ | $\nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$ |
| Gauss' Law     | $\iint_S \vec{B} \cdot d\vec{S} = 0$  | $\nabla \cdot \vec{B} = 0$                              |
| Gauss' Law     | $\iint_S \vec{D} \cdot d\vec{S} = \iiint_V \rho dV$   | $\nabla \cdot \vec{D} = \rho$                           |
| Continuity Eq. | $\iint_S \vec{J} \cdot d\vec{S} = -\frac{d}{dt} \iiint_V \rho dV$   | $\nabla \cdot \vec{J} = -\frac{d\rho}{dt}$              |

Goddard ECE329  
Cumulative Review

26

\* Important

## Realizable Fields

- Is it time dependent ( $d/dt$ )?
- Is there any free charge  $\rho$  or current density  $\vec{J}$ ?
- Apply Maxwell's equations

$$\nabla \cdot \vec{D} = \rho \quad \nabla \cdot \vec{B} = 0 \quad \nabla \cdot \vec{J} = -\frac{d\rho}{dt}$$

$$\nabla \times \vec{E} = -\frac{d\vec{B}}{dt} \quad \nabla \times \vec{H} = \vec{J} + \frac{d\vec{D}}{dt}$$

$$\vec{D} = \epsilon \vec{E} \quad \vec{B} = \mu \vec{H}$$

Goddard ECE329  
Cumulative Review

27

## Field Source

- Infinite plane sheet of current at  $z=0$

$\vec{J}_s = -J_s(t) \vec{a}_x$

At  $z=0$

Goddard ECE329  
Cumulative Review

## Solution

$$\vec{E}(z, t) = \frac{\eta_0}{2} J_s(t \mp \frac{z}{v_p}) \vec{a}_x \quad z \gtrless 0$$

$$\vec{H}(z, t) = \pm \frac{1}{2} J_s(t \mp \frac{z}{v_p}) \vec{a}_y$$

Goddard ECE329  
Cumulative Review

\* Important

## Two definitions

$$v_p = c = \frac{1}{\sqrt{\mu_0 \epsilon_0}} = \text{speed of light} = 3 \times 10^8 \text{ (m/s)}$$


$$\eta_0 = \sqrt{\frac{\mu_0}{\epsilon_0}} \approx 377 \text{ (ohms)} \quad \text{Intrinsic impedance of free space}$$

$$|\vec{E}| = \eta_0 |\vec{H}|$$

Goddard ECE329  
Cumulative Review

\* Important

## Web Demo



<http://www.phy.ntnu.edu.tw/java/emWave/emWave.html>

Goddard ECE329  
Cumulative Review

\* Important

## Sinusoidal Plane Waves

$$\vec{J}_s = -J_{s0} \cos(\omega t) \hat{a}_x \quad \vec{E}(z, t) = \frac{\eta_0}{2} J_s(t \mp \frac{z}{v_p}) \hat{a}_x \quad \vec{H}(z, t) = \pm \frac{1}{2} J_s(t \mp \frac{z}{v_p}) \hat{a}_y$$

$$\vec{E}(z, t) = \frac{\eta_0 J_{s0}}{2} \cos(\omega t \mp \beta z) \hat{a}_x \quad z \geq 0$$

$$\vec{H}(z, t) = \pm \frac{J_{s0}}{2} \cos(\omega t \mp \beta z) \hat{a}_y \quad \beta = \frac{\omega}{v_p}$$

Goddard ECE329  
Cumulative Review

\*\* Very Important

## Wave Parameters

$$\vec{E}(z, t) = \frac{\eta_0 J_{s0}}{2} \cos(\omega t \mp \beta z) \hat{a}_x$$

Phase  $\phi = \omega t \mp \beta z$  (radians)

Angular Frequency  $\omega = \frac{\partial \phi}{\partial t}$  (radians/sec)

Linear Frequency  $f = \frac{\omega}{2\pi}$  (1/sec)

Phase Constant  $\beta = \mp \frac{\partial \phi}{\partial z}$  (radians/m)

Wavelength  $\lambda = \frac{2\pi}{\beta}$  (m)

Phase Velocity  $v_p \equiv \frac{\omega}{\beta} = \lambda f = c$  (m/sec)


Impedance  $\eta_0 = |\vec{E}| / |\vec{H}|$  ( $\Omega$ )

Goddard ECE329  
Cumulative Review

\* Important

## Polarization

### Linear



DIRECTION: Constant  
MAGNITUDE: Varies

$$\vec{F}_1 = F_1 \cos(\omega t + \phi) \hat{a}_x$$


$$\vec{F}_2 = \pm F_2 \cos(\omega t + \phi) \hat{a}_y$$

The vectors are IN PHASE



Goddard ECE329  
Cumulative Review

### Circular




DIRECTION: Varies  
MAGNITUDE: Constant

$$\vec{F}_1 = F_0 \cos(\omega t + \phi) \hat{a}_x$$

$$\vec{F}_2 = F_0 \sin(\omega t + \phi) \hat{a}_y$$

The vectors must be:  
EQUAL MAGNITUDE  
OUT OF PHASE by  $\frac{\pi}{2}$   
PERPENDICULAR


Left/right thumb points in propagation direction



"Left-Hand" Polarized CCW as seen by source

"Right-Hand" Polarized CW as seen by source

### Elliptical



DIRECTION: Varies  
MAGNITUDE: Varies

Most general:  
If it is not linear or circular

## Writing Fields in Free Space

- Sinusoidal field propagating in  $\hat{a}_z$  has left circular polarization,  $\lambda=3\text{m}$ ,  $E(0,0)=E_0 \hat{a}_y$



- Answer:  $\beta=2\pi/\lambda=2\pi/3 \text{ rad/m}$ ;
- $\lambda f=c \rightarrow f=1\times 10^8 \text{ Hz} \rightarrow \omega=2\pi f=2\pi \times 10^8 \text{ rad/s}$
- $E_y$  is max first then  $\frac{1}{4}$  period later  $E_x$  is max
- $E=E_0 \cos(\omega t - \beta z) \hat{a}_y + E_0 \sin(\omega t - \beta z) \hat{a}_x$
- $H=H_0/\eta_0 \cos(\omega t - \beta z) (-\hat{a}_x) + H_0/\eta_0 \sin(\omega t - \beta z) \hat{a}_y$

35

Goddard ECE329  
Cumulative Review

\* Important

## Definition: Poynting Vector

The  $\mathbf{E}$  and  $\mathbf{H}$  fields are carrying power with them as they propagate

$$\vec{S} = \vec{E} \times \vec{H}$$

Definition for the Power Flow Density of an EM Field

Units for  $\mathbf{S}$ : Watts/m<sup>2</sup>

$$\oint_S \vec{S} \bullet d\vec{S} = \oint_S (\vec{E} \times \vec{H}) \bullet d\vec{S}$$

Power flow out of a CLOSED surface (units = Watts)

Goddard ECE329  
Cumulative Review

\* Important

## Poynting's Theorem

$$\oint_S \vec{S} \cdot d\vec{S} = -\frac{\partial}{\partial t} \iiint_V (w_m + w_e) dV - \iiint_V \vec{E} \cdot \vec{J} dV$$

Power flow OUT of surface = Rate of field energy LOSS and Rate of work done BY the fields

$$w_m = \frac{1}{2} \mu_0 H^2 \text{ stored magnetic energy density}$$

$$w_e = \frac{1}{2} \epsilon_0 E^2 \text{ stored electric energy density}$$

$$\vec{E} = \operatorname{Re}[\vec{E}(z)e^{j\omega t}], \vec{H} = \operatorname{Re}[\vec{H}(z)e^{j\omega t}]$$


$$\langle \vec{S} \rangle = \operatorname{Re}\left[\frac{1}{2} \vec{E} \times \vec{H}^*\right]$$

Goddard ECE329  
Cumulative Review

## 3 types of materials

Chapter 4

### Conductors




**Free electrons**  
**Bound electrons**

$\mathbf{E}=0$  inside  
 $\rho_s=0$  inside  
 $\rho_s$  only surface charge  
 $V$  is same throughout  
 $\mathbf{E}_{\text{outside}}$  is  $\perp$  to surface

Goddard ECE329  
Cumulative Review


### Dielectrics



## 3 types of materials

Chapter 4

### Magnetic




**Bound electrons**  
**Magnetic moments**

$\mathbf{B}_{\text{tot}}=\mathbf{B}_s+\mathbf{B}_b$   
 $\mathbf{B}_{\text{tot}}=\mu \mathbf{H}=\mu_0(\mathbf{H}+\mathbf{M})$

$\mathbf{E}=0$  inside but it is reduced  
 $\mathbf{E}_{\text{tot}}=\mathbf{E}_a+\mathbf{E}_s$   
 $\mathbf{D}=\epsilon \mathbf{E}_{\text{tot}}=\mathbf{P}+\epsilon_0 \mathbf{E}_{\text{tot}}$

Goddard ECE329  
Cumulative Review

## Conducting Slab D4.2 (p217)




- Neutral slab  $\rightarrow \rho_1 = -\rho_2$
- $\mathbf{E}_{\text{inside}} = 0 \rightarrow E_z = (\rho_B + \rho_2 - \rho_A - \rho_1) / 2\epsilon_0 = 0$

$$\rho_1 = (\rho_B - \rho_A)/2, \rho_2 = (\rho_A - \rho_B)/2$$

Goddard ECE329  
Cumulative Review


## Dielectric Slab



Goddard ECE329  
Cumulative Review

## Magnetic Sheets D4.6 (p238)

- Hint (Single infinite current sheet)



Goddard ECE329  
Cumulative Review

\*\*\* Extremely Important  
Inside a material, Maxwell's Equations become:

### Free Space

$$\nabla \times \vec{H} = \vec{J} + \frac{\partial \vec{D}}{\partial t}$$

$$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

$$\vec{\nabla} \bullet \vec{D} = \rho$$

$$\vec{\nabla} \bullet \vec{B} = 0$$

### Inside Material

$$\nabla \times \vec{H} = \sigma \vec{E} + \epsilon \frac{\partial \vec{E}}{\partial t}$$

$$\nabla \times \vec{E} = -\mu \frac{\partial \vec{H}}{\partial t}$$

$$\vec{\nabla} \bullet (\epsilon \vec{E}) = \rho$$

$$\vec{\nabla} \bullet \vec{H} = 0$$

Goddard ECE329  
Cumulative Review

\* Important

## Solve PDEs with Phasors

- Technique simplifies the algebra

$$E_x(z, t) = \operatorname{Re}[\bar{E}_x(z)e^{j\omega t}]$$

$$\frac{\partial E_x}{\partial t} = \operatorname{Re}[j\omega \bar{E}_x(z)e^{j\omega t}]$$

$$\left. \begin{aligned} \frac{\partial E_x}{\partial z} &= -\mu \frac{\partial H_y}{\partial t} \\ \frac{\partial H_y}{\partial z} &= -\sigma E_x - \varepsilon \frac{\partial E_x}{\partial t} \end{aligned} \right\} \quad \left. \begin{aligned} \frac{\partial \bar{E}_x}{\partial z} &= -\mu(j\omega) \bar{H}_y \\ \frac{\partial \bar{H}_y}{\partial z} &= -\sigma \bar{E}_x - \varepsilon(j\omega) \bar{E}_x \end{aligned} \right.$$

Goddard ECE329  
Cumulative Review

\*\* Very Important

## Final Solution for $E_x$ and $H_y$

$$\bar{E}(z, t) = \frac{|\bar{\eta}| J_{S0}}{2} e^{\mp \alpha z} \cos(\omega t \mp \beta z + \tau) \hat{a}_x$$

$$\bar{H}(z, t) = \frac{\pm J_{S0}}{2} e^{\mp \alpha z} \cos(\omega t \mp \beta z) \hat{a}_y \quad z \geq 0$$


Magnitude of  $E$  and  $H$  related through magnitude of the complex impedance,  $\bar{\eta}$

Strength of fields drops exponentially according to the attenuation constant

$E$  and  $H$  are out of phase by the phase of the complex impedance,  $\tau$

Goddard ECE329  
Cumulative Review

\* Important



Goddard ECE329  
Cumulative Review

\* Important

## Complex Propagation Constant and Impedance

$$\frac{\partial \bar{E}_x^2}{\partial z^2} = \bar{\gamma}^2 \bar{E}_x \quad \bar{\gamma} = \sqrt{j\omega\mu(\sigma + j\omega\varepsilon)} = \alpha + j\beta = |\bar{\gamma}| e^{j\psi}$$

$\bar{\gamma}^2$  is in Quadrant II  
 $\therefore \beta > \alpha > 0$

$$\operatorname{Re}[\bar{\gamma}^2] < 0, \operatorname{Im}[\bar{\gamma}^2] > 0$$

$$\Rightarrow 45^\circ \leq \psi \leq 90^\circ$$

$$\therefore \beta > \alpha > 0$$

$$\bar{\eta} = \sqrt{\frac{j\omega\mu}{\sigma + j\omega\varepsilon}} = |\bar{\eta}| e^{j\tau}$$

$$\text{Phase diff. between } E \text{ and } H$$

$$\bar{\eta} \bar{\eta} = j\omega\mu \Rightarrow \tau + \psi = \pi/2$$

$$\bar{\gamma}/\bar{\eta} = \sigma + j\omega\varepsilon$$

Very useful!

Goddard ECE329  
Cumulative Review

\*\* Very Important

## Dielectrics vs Conductors

### Perfect Dielectric

Definition:  $\sigma = 0$

Attenuation:  $\alpha = 0$

Speed:  $v_p = c / \sqrt{\mu_r \epsilon_r} \leq c$

$E, H$  In Phase:  $\tau = 0$

Impedance:  $|\bar{\eta}| = \eta_0 \sqrt{\mu_r / \epsilon_r}$

### Imperfect Dielectric

Definition:  $\sigma / \omega \epsilon \ll 1$

Attenuation:  $\alpha \approx \sigma / 2\sqrt{\mu_r / \epsilon_r}$

Speed:  $v_p \approx c / \sqrt{\mu_r \epsilon_r} \leq c$

$E, H$  In Phase:  $\tau \approx 0$

Impedance:  $|\bar{\eta}| \approx \eta_0 \sqrt{\mu_r / \epsilon_r}$

### Good Conductor

Definition:  $\sigma / \omega \epsilon \gg 1$

Attenuation:  $\alpha \approx \sqrt{\omega\mu\sigma / 2}$

Speed:  $v_p \approx \sqrt{2\omega / \sigma\mu}$

$E, H$  45° Phase:  $\tau \approx \pi/4$

Impedance:  $|\bar{\eta}| \approx \sqrt{\omega\mu / \sigma}$

### Perfect Conductor

Definition:  $\sigma \rightarrow \infty$

Attenuation:  $\alpha \rightarrow \infty$

Speed:  $v_p \rightarrow 0$


$E, H$  45° Phase:  $\tau \rightarrow \pi/4$

Impedance:  $|\bar{\eta}| \rightarrow 0$

\*\* Very Important

## Boundary Conditions

- Never use the differential form of Maxwell's equations at a boundary – only use integral form



Goddard ECE329  
Cumulative Review

Chapter 5

### Example: Potentials for a Point Charge

$\vec{E} = \frac{Q}{4\pi\epsilon_0 r^2} \hat{a}_r \quad \vec{E} = -\nabla V$

$V(r) = - \int_{\infty}^{r_i} \vec{E} \bullet d\vec{l}$  "Absolute" potential at  $r_i$  using zero potential at  $r = \infty$

$d\vec{l} = -|dr| \hat{a}_r = dr \hat{a}_r$  Since  $dr < 0$  going from  $r = \infty$

$V(r) = - \int_{\infty}^{r_i} \frac{Q}{4\pi\epsilon_0 r^2} dr$

$$= \frac{Q}{4\pi\epsilon_0} \left( \frac{1}{r_i} - \frac{1}{\infty} \right) = \frac{Q}{4\pi\epsilon_0 r_i}$$

Surfaces of constant potential are spheres in 3D - same amount of work

Goddard ECE329 Cumulative Review

### Superposition Example: Potential of a Line Charge

$\rho_l = 10^{-10} (C/m)$        $a = 1m$

Find Potential at point "P", 1 m away from the line

$V_p = \frac{1}{4\pi\epsilon_0} \int_a^{-a} \frac{dQ}{r}$

$V_p = \frac{1}{4\pi\epsilon_0} \int_a^{-a} \frac{\rho_l dz'}{r}$

$V_p = \frac{1}{4\pi\epsilon_0} \int_a^{-a} \frac{\rho_l dz'}{\sqrt{z'^2 + 1}}$

$V_p = \frac{\rho_l}{4\pi\epsilon_0} \ln(z' + \sqrt{z'^2 + 1}) \Big|_{-a}^a$

Goddard ECE329 Cumulative Review

### Example 5.5 (p-n junction)

$\nabla^2 V = -\rho/\epsilon$

$\vec{E} = -\nabla V$

$E = \int_{-x}^x \frac{\rho}{\epsilon} dx$

$V = - \int_{-x}^x E dx$

$-d_p \quad eN_D \quad d_n \quad -eN_A$

$\frac{dE}{dx} = \frac{\rho}{\epsilon}$

$\frac{dV}{dx} = -E$

Goddard ECE329 Cumulative Review

\*\* Very Important

### Steps to Find Capacitance

$x=d, V=V_0$        $x=0, V=0$

$E = \frac{V}{d}$

$\nabla^2 V = 0$

Find  $V$  using boundary conditions

Find  $E$  using  $\vec{E} = -\vec{\nabla}V$

Find  $D$  using  $\vec{D} = \epsilon \vec{E}$

Get surface charge density on one conductor using BC  $\rho_s = \vec{a}_n \bullet (\vec{D}_{n1} - \vec{D}_{n2})$

Charge  $Q = (\text{Area})(\rho_s)$

Capacitance  $C = Q/V_0$

$V(x) = V_0 \frac{x}{d}$

$C = \frac{\epsilon A}{d}$

Goddard ECE329 Cumulative Review

### Coaxial Cable

$\nabla^2 V = \frac{1}{r} \frac{\partial}{\partial r} \left( r \frac{\partial V}{\partial r} \right) = 0$

$\Rightarrow r \frac{\partial V}{\partial r} = c_1 \Rightarrow V_r = c_1 \ln r + c_2$

$V(b) = 0 \Rightarrow c_2 = -c_1 \ln b$

$V(a) = V_0 \Rightarrow c_1 = V_0 / \ln(a/b)$

$V(r) = -V_0 \frac{\ln(r/b)}{\ln(b/a)}$

$E = \frac{-dV}{dr} = \frac{V_0}{r \ln(b/a)}$

$\rho = \begin{cases} \epsilon V_0 / (a \ln(b/a)), & r = a \\ -\epsilon V_0 / (b \ln(b/a)), & r = b \end{cases}$

$C = \frac{2\pi\epsilon L}{\ln(b/a)}$

Goddard ECE329 Cumulative Review

### Inductance of a Coax Cable


Now, instead of applying a voltage across the inner and outer conductor, a current,  $I$ , flows down the length of the outer conductor and returns in the opposite direction through the inner conductor

Results in magnetic field  $H_\phi = \frac{I}{2\pi r}$

in between the coax

Goddard ECE329 Cumulative Review

## Inductance of Coaxial Cable



$$\vec{B} = \mu \vec{H} = \frac{\mu I}{2\pi r} \vec{a}_\phi \quad \text{Magnetic Flux Density} \quad \left[ \frac{Wb}{m^2} \right]$$

$$\psi = \int B \cdot dS = \int_{r=a}^b \int_{z=0}^L \left( \frac{\mu I}{2\pi r} \right) (dr dz) \quad \text{Magnetic Flux} \quad [Wb]$$

$$\psi = \frac{\mu L z}{2\pi} \ln(b/a)$$

Goddard ECE329  
Cumulative Review

## Inductance

$$L = \frac{\psi}{I} \quad \text{Units: Henry (H)}$$

$$L = \frac{\mu z}{2\pi} \ln(b/a)$$

$$\mathcal{L} = \frac{L}{z} = \frac{\mu}{2\pi} \ln(b/a) \quad \text{Inductance/Length (H/m)}$$

Goddard ECE329  
Cumulative Review

## \* Important Relationships between Capacitance, Conductance & Inductance

Notice in the above examples,

$$\mathcal{C} = \epsilon \cdot \text{GeometricalFactor}$$

$$\mathcal{L} = \mu / \text{GeometricalFactor}$$

$$\mathcal{G} = \sigma \cdot \text{GeometricalFactor}$$

This is true in general and so we have the following:


$$\mathcal{LC} = \mu \epsilon \quad \mathcal{G}/\mathcal{C} = \sigma / \epsilon$$

If you know one (L, C, or G), you can find the other two from the material parameters

Goddard ECE329  
Cumulative Review

Chapter 6

## Transmission Line



$V(z,t)$  and  $I(z,t)$  can be used to describe the state of the transmission line instead of  $E_x(z,t)$  and  $H_y(z,t)$

Goddard ECE329  
Cumulative Review

## Transmission Line Equations


$$\begin{aligned} \frac{\mathcal{V}}{\partial z} &= -\left(\frac{\mu d}{w}\right) \frac{\partial I}{\partial z} & \left\{ \begin{aligned} \frac{\mathcal{V}}{\partial z} &= -\mathcal{L} \frac{\partial I}{\partial z} \\ \frac{\partial I}{\partial z} &= -\left(\frac{\epsilon w}{d}\right) \frac{\partial \mathcal{V}}{\partial z} \end{aligned} \right. \\ \frac{\partial I}{\partial z} &= -\left(\frac{\epsilon w}{d}\right) \frac{\partial \mathcal{V}}{\partial z} \end{aligned}$$

- These are the transmission line equations!!  
 • They describe wave propagation along the TL in terms of currents and voltages  
 • It is just another way of stating Maxwell's Eqns

Goddard ECE329  
Cumulative Review

\*\* Very Important

## Bounce Diagram









First step: Calculate  $V^+$ ,  $I^+$ ,  $\Gamma_{load}$ ,  $\Gamma_{source}$

$$V^+ = V_0 \frac{Z_0}{R_s + Z_0} = 100 \frac{60}{40 + 60} = 60V \quad \Gamma_L = \frac{R_L - Z_0}{R_L + Z_0} = \frac{120 - 60}{120 + 60} = \frac{1}{3}$$


$$I^+ = \frac{V^+}{Z_0} = \frac{60}{60} = 1A \quad \Gamma_s = \frac{R_s - Z_0}{R_s + Z_0} = \frac{40 - 60}{40 + 60} = -\frac{1}{5}$$

Second step: Construct 2 bounce diagrams  
(Voltage and Current)


Goddard ECE329  
Cumulative Review



## Transmission Line Junction



Equivalent circuit "seen" by  $V^+$  when it gets to the end of line 1:




$$\Gamma = \frac{V^-}{V^+} = \frac{R_L - Z_{01}}{R_L + Z_{01}}$$


$$R_L = (R_1) \parallel (R_2 + Z_{02})$$

What is  $R_L$  for this equivalent circuit?

Goddard ECE329  
Cumulative Review



How much voltage gets transmitted through to line 2?



$$\tau_v = \frac{V^{++}}{V^+} = 1 + \Gamma$$


$$V^{++} = V^+ (1 + \Gamma)$$

$$V_{trans} = \frac{Z_{02}}{Z_{02} + R_2} V^{++}$$

Goddard ECE329  
Cumulative Review

Optional

## Inductive Termination



$$V^+ = \frac{V_0}{2}$$

$$I^- = -\frac{V^-(t)}{Z_0}$$

$$I^+ = \frac{V^+}{Z_0} = \frac{V_0}{2Z_0}$$

For the inductor:

$$V = L \frac{dI}{dt}$$

Goddard ECE329  
Cumulative Review

Optional

## Diff Eqn for the Inductor

$$V = L \frac{dI}{dt} \Rightarrow (V^+ + V^-(t)) = L \frac{d(I^+ + I^-(t))}{dt}$$

$$\frac{V_0}{2} + V^-(t) = L \frac{d}{dt} \left( \frac{V_0}{2Z_0} - \frac{V^-(t)}{Z_0} \right)$$

$$\frac{V_0}{2} = -\frac{L}{Z_0} \frac{dV^-(t)}{dt} - V^-(t)$$

$$\frac{dV^-(t)}{dt} + \frac{Z_0}{L} V^-(t) = -\frac{Z_0}{L} \frac{V_0}{2}$$

Laplace Transform  $V(t')$  to  $F(s)$

$$s\hat{V}^-(s) - V^-(0) + \frac{Z_0}{L}\hat{V}^-(s) = -\frac{Z_0}{L} \frac{V_0}{2} \frac{1}{s}$$

$t' = t - T$

Goddard ECE329  
Cumulative Review

Optional

## Laplace Transform for Inductor

Initial Condition At  $t=T$ , i.e.  $t'=0$ , inductor current = 0 since inductor "looks" like an OPEN CIRCUIT

$$I = I^+ + I^-(T) = 0 \Rightarrow \frac{V_0}{2Z_0} - \frac{V^-(0)}{Z_0} = 0 \Rightarrow V^-(0) = V_0/2$$

$$s\hat{V}^-(s) - \frac{V_0}{2} + \frac{Z_0}{L}\hat{V}^-(s) = -\frac{Z_0}{L} \frac{V_0}{2} \frac{1}{s} \Rightarrow \hat{V}^-(s) = \frac{sL - Z_0}{sL + Z_0} \frac{V_0}{2s}$$

In s-space, we have  $V(s) = \Gamma(s) V^+(s)$  with:

$$\Gamma(s) = \frac{Z(s) - Z_0}{Z(s) + Z_0}$$

$$\hat{V}^+(s) = \frac{V_0}{2s}$$

$Z(s) = sL$  for an inductor


Goddard ECE329  
Cumulative Review

Optional





## Invert Laplace Transform

$$\hat{V}(s) = \hat{V}^+ + \hat{V}^- = \frac{V_0}{2s} + \frac{V_0}{2s} \frac{sL - Z_0}{sL + Z_0} = \frac{V_0}{2s} \frac{2sL}{sL + Z_0} = \frac{V_0}{s + Z_0/L}$$

$$V(t) = V_0 e^{-(Z_0/L)t} = V_0 e^{-(Z_0/L)(t-T)} \quad t > T$$



Goddard ECE329  
Cumulative Review



*\* Important*

*Chapter 7*

### Phasors satisfy usual TL equations

$$\left. \begin{aligned} \frac{\partial V}{\partial z} &= -\mathcal{L} \frac{\partial I}{\partial t} \\ \frac{\partial I}{\partial z} &= -\mathcal{C} \frac{\partial V}{\partial t} \end{aligned} \right\} \quad \left. \begin{aligned} \frac{d\bar{V}}{dz} &= -\mathcal{L}(j\omega \bar{I}) \\ \frac{d\bar{I}}{dz} &= -\mathcal{C}(j\omega \bar{V}) \end{aligned} \right\} \quad \left. \begin{aligned} \frac{d\bar{V}}{dz} &= -\mathcal{L}\mathcal{C}\omega^2 \bar{V} \\ \frac{d\bar{I}}{dz} &= -\mathcal{L}\mathcal{C}\omega^2 \bar{I} \end{aligned} \right\}$$

$$\begin{aligned} \bar{V} &= V^\pm e^{\mp j\beta z} \\ \bar{I} &= \pm \frac{V^\pm}{Z_0} e^{\mp j\beta z} \end{aligned} \quad \begin{aligned} \beta &= \omega \sqrt{\mathcal{L}\mathcal{C}} \\ Z_0 &= \sqrt{\mathcal{L}/\mathcal{C}} \end{aligned} \quad \begin{aligned} \bar{V} &= V^+ e^{j\beta d} + V^- e^{-j\beta d} \\ \bar{I} &= \frac{1}{Z_0} (V^+ e^{j\beta d} - V^- e^{-j\beta d}) \end{aligned}$$

77

Goddard ECE329 Cumulative Review

*\*\* Very Important*

### Key Definition: Line Impedance

$$Z(d) \equiv \frac{\bar{V}(d)}{\bar{I}(d)}$$

$$Z(d) = Z_0 \frac{1 + \Gamma_L e^{-2j\beta d}}{1 - \Gamma_L e^{-2j\beta d}}$$

Equivalent Circuit

$V(d)$

$I(d)$

$Z_g$

$Z_0$

$Z(d)$

$F=V_g$

$d=l$

$$V(l) = F \frac{Z(l)}{Z(l) + Z_g} = V^+ (e^{j\beta l} + \Gamma_L e^{-j\beta l})$$

Allows you to solve for  $V^+$  and thus get  $V(d,t)$  and  $I(d,t)$

78

Goddard ECE329 Cumulative Review

*\*\* Very Important*

## Key Definition: Generalized Reflection Coefficient

$$\Gamma(d) \equiv \frac{\bar{V}^-(d)}{\bar{V}^+(d)}$$

$$\Gamma(d) = \frac{V^- e^{-j\beta d}}{V^+ e^{j\beta d}} = \Gamma_L e^{-2j\beta d}$$

Allows you to find the backwards wave if forward wave is known

79

Goddard ECE329  
Cumulative Review

*\*\* Very Important*

## Key Definitions: Admittance and Normalized Impedance

Characteristic Admittance

$$Y_0 \equiv \frac{1}{Z_0}$$

Normalized Impedance

$$z(d) \equiv \frac{Z(d)}{Z_0}$$

$$z(d) = \frac{1+\Gamma(d)}{1-\Gamma(d)}$$

Normalized Admittance

$$y(d) \equiv \frac{1}{z(d)}$$

$$y(d) = \frac{1-\Gamma(d)}{1+\Gamma(d)}$$

$$\Gamma(d) = \Gamma_L e^{-2j\beta d}$$

80

Goddard ECE329  
Cumulative Review

*\*\*\* Extremely Important*

## Summary of TL Equations

$$\Gamma_L = \frac{Z_L - Z_0}{Z_L + Z_0}$$

$$V^- = \Gamma_L V^+$$

$$\Gamma(d) = \Gamma_L e^{-2j\beta d}$$

$$\bar{V}(d) = V^+ e^{j\beta d} (1 + \Gamma_L e^{-2j\beta d}) = V^+ e^{j\beta d} (1 + \Gamma(d))$$

$$\bar{I}(d) = \frac{V^+ e^{j\beta d}}{Z_0} (1 - \Gamma_L e^{-2j\beta d}) = \frac{V^+ e^{j\beta d}}{Z_0} (1 - \Gamma(d))$$

$$Z(d) \equiv \frac{\bar{V}(d)}{\bar{I}(d)} = Z_0 \frac{1 + \Gamma(d)}{1 - \Gamma(d)}$$

$$z(d) = \frac{1 + \Gamma(d)}{1 - \Gamma(d)}$$

$$y(d) \equiv \frac{1}{z(d)} = z(d) \pm \frac{\lambda}{4}$$

$$\Gamma(d) = \frac{z(d) - 1}{z(d) + 1}$$

81

Goddard ECE329  
Cumulative Review


*\*\*\* Extremely Important*

## Smith Chart

$$\Gamma = \frac{z - 1}{z + 1}$$

$$z = r + jx$$


S.C. is a map between the half-plane  $r \geq 0$  and the disc  $|\Gamma| \leq 1$



PrintFreeGraphPaper.com  
© Analog Instruments Company  
Used with permission

*\* Important*

## Standing Waves for SC Line



$$\bar{V}(d) = V^+ (e^{j\beta d} - e^{-j\beta d}) = 2jV^+ \sin(\beta d)$$

$$\bar{I}(d) = \frac{V^+}{Z_0} (e^{j\beta d} + e^{-j\beta d}) = 2Y_0 V^+ \cos(\beta d)$$

$$Z(d) \equiv \frac{\bar{V}(d)}{\bar{I}(d)} = jZ_0 \tan \beta d$$

83

Goddard ECE329  
Cumulative Review

*\* Important*

## Standing Waves for SC Line


$$V(d,t) = -2V^+ |\sin(\beta d)| \sin(\omega t + \theta)$$

$$I(d,t) = 2Y_0 V^+ |\cos(\beta d)| \cos(\omega t + \theta)$$

$$V(0,t) = 0 \text{ always (voltage null)}$$

$$I(0,t) \text{ varies (current maxima)}$$

Dependence is different than traveling wave:  $\omega t \pm \beta z$




84

Goddard ECE329  
Cumulative Review

## Input Impedance for SC Line

$$Z_{in} = Z(l) = jZ_0 \tan \beta l$$



85

Goddard ECE329  
Cumulative Review


\* Important

SC Line can act as an inductor or a capacitor depending on  $\beta l$


$$Z_{in} = jZ_0 \tan \beta l$$

If  $\tan(\beta l) > 0$ , shorted TL is inductive

If  $\tan(\beta l) < 0$ , shorted TL is capacitive



e.g.  $\beta l < \pi/2$   
or  $l < \lambda/4$ , TL is inductive



Equivalent Circuit:  
L


86

Goddard ECE329  
Cumulative Review

For  $\beta l = 0, \pi, 2\pi, \dots$  TL is a short  
For  $\beta l = \pi/2, 3\pi/2, \dots$  TL is an open

$$Z_{in} = jZ_0 \tan \beta l = \begin{cases} 0 = a \text{ short for } \beta l = n\pi, n = 0, 1, 2, \dots \\ \infty = a \text{ open for } \beta l = (n+1/2)\pi \end{cases}$$

If  $Z_{in}=0$ , voltage drop is zero, just like a short  
If  $Z_{in}=\infty$ , current is zero, just like an open



87

Goddard ECE329  
Cumulative Review

## Standing Waves for OC Line


Same phasor algebra as before  
with current & voltage reversed!

$$I(d, t) = -2Y_0 |V^+| \sin(\beta d) \sin(\omega t + \theta)$$

$$V(d, t) = 2|V^+| \cos(\beta d) \cos(\omega t + \theta)$$

$I(0, t) = 0$  always (current null)  
 $V(0, t)$  varies (voltage maxima)

Goddard ECE329  
Cumulative Review




88

For  $\beta l = 0, \pi, 2\pi, \dots$  TL is an open  
For  $\beta l = \pi/2, 3\pi/2, \dots$  TL is a short

$$Y_{in} = jY_0 \tan \beta l = \begin{cases} 0 = a \text{ open for } \beta l = n\pi, n = 0, 1, 2, \dots \\ \infty = a \text{ short for } \beta l = (n+1/2)\pi \end{cases}$$

If  $Y_{in}=0$ , current is zero, just like an open  
If  $Y_{in}=\infty$ , voltage drop is zero, just like a short



89

Goddard ECE329  
Cumulative Review


\* Important

## Parallel & Series Resonances

- We can find  $\lambda_n$  and  $\omega_n$  by applying the appropriate BCs at both ends

- Series resonance if  $z_{in}(l)=0$

- Analogous to an LC circuit in series and requires a short placed across TL at  $d=l$
- Like a short input









90

- Parallel resonance:  $y_{in}(l)=0$

- Analogous to an LC circuit in parallel and requires an open across the TL at  $d=l$

- Like an open input

Goddard ECE329  
Cumulative Review




Repeat D7.8a  
(p 472):

$$z(0)=0.5$$


Thus, we need a stub with  $y_s(l_s)=0.72j$  at a distance of  $0.098\lambda$  from load

Goddard ECE329  
Cumulative Review



Optional

### Double Stub Matching w/ S.C.



Key Observations:

1. For a match,  $y_2'$  must be on unit conductance circle
2. Thus,  $y_1$  is on the auxiliary circle
  - AUXILIARY CIRCLE is UCC pivoted CCW towards the load by  $d_{12}$

99

Goddard ECE329  
Cumulative Review

Find length for shorted stub:  
 $y(l_s)=0.72j$

$$z(0)=0$$

$$y(0)=\infty$$

$$l_s = (0.25 + 0.098)\lambda$$

$$l_s = 0.348\lambda$$


or use:

$$l_s = \frac{\lambda}{2\pi} \tan^{-1}(-\frac{1}{b}) \bmod \lambda/2$$

$$l_s = -0.151\lambda = 0.349\lambda$$

Goddard ECE329  
Cumulative Review

Repeat DSM:  $d_1=0$ ,  
 $d_{12}=0.375\lambda$   
 $z(0)=0.6-0.8j$



To get  $y_1'$  on UCC, need  $y_1$  on AUX so draw AUX first using given  $d_{12}$


Goddard ECE329  
Cumulative Review

Repeat DSM:  $d_1=0$ ,  
 $d_{12}=0.375\lambda$   
 $z(0)=0.6-0.8j$

$$y(0)=0.6+0.8j$$

Since  $d_1=0$ ,  
 $y_1=y(0)$

Goddard ECE329  
Cumulative Review



101


Find susceptance to jump  
from  $y_1$  along constant  
conductance circle to  
 $y_1$  on AUX

$$b_s = -0.89 \text{ or } b_s = -2.72$$


$$l_s = \frac{\lambda}{2\pi} \tan^{-1}(-\frac{1}{b})$$

$$l_s = 0.134\lambda \text{ or } l_s = 0.056\lambda$$

Goddard ECE329  
Cumulative Review




102



Optional

## Double Stub Matching


- Double stub matching inserts two shorted stub of impedance  $Z_0$  with specific lengths,  $l_1$  and  $l_2$ , at fixed spots,  $d_1$  and  $d_1 + d_{12}$ , from the load



- Go from  $y(0)$  to  $y_1'$  a distance  $d_1$  along  $|\Gamma(0)|$  circle. Find  $b_1$  by going from  $y_1'$  along constant conductance circle to  $y_1$  which is on the AUX circle. Find  $y_2$  by pivoting AUX by  $d_{12}$  to UCC and read off  $b_2 = -\text{Im}(y_2)$ .

$$\text{Calculate } l_1 \text{ and } l_2 \text{ using: } l_s = \frac{\lambda}{2\pi} \tan^{-1}\left(-\frac{1}{b}\right) \bmod \lambda/2$$

Goddard ECE329 Cumulative Review




## Distributed Circuit of Lossy TL

Model the Ohmic losses in conducting wires and leakage losses in the imperfect dielectric in between


One slice of the lossy TL:

$$\frac{\partial V}{\partial z} = -(j\omega L + R)I$$

$$\frac{\partial I}{\partial z} = -(j\omega C + G)V$$



Goddard ECE329 Cumulative Review



107

Good luck on the final!

- It was a pleasure teaching ECE329 this semester  
–Thank you for studying so hard ☺

Goddard ECE329 Cumulative Review

108