PrismGo GPS Push API

BlackPrism · Version 1.0 · 16 October 2026

Uffizio pushes each tracker's position to one PrismGo HTTPS endpoint as soon as it is recorded, in the JSON format below. This replaces our polling of the token-based Pull API.

Overview

PrismGo is BlackPrism's vehicle request and live tracking system. It uses positions to show vehicles on a live map, estimate arrival times, and start and end trips automatically when a vehicle leaves the pickup and reaches the drop.

- **Sender:** Uffizio, for every tracker on the client's account.
- **Receiver:** PrismGo, one endpoint for all vehicles.
- **Matching:** each position is matched to a vehicle by the tracker's IMEI.
- **Until push is live:** PrismGo keeps polling the Pull API, so nothing is lost while we test.

Endpoint and authentication

Item	Value
Method	`POST`
URL	`https://api.prismgo.blackprism.in/api/v1/gps/webhook` (live now for testing; we will confirm if the production address changes)
Content type	`Content-Type: application/json`
Authentication	Header `X-GPS-Secret: <shared secret>`
Transport	HTTPS only, TLS 1.2 or later

We will send the shared secret separately, not by email in plain text. Keep it on your server only. Requests without it, or with a wrong one, are refused with `401`.

If you need to allow our address in a firewall, or need us to allow yours, tell us the IP addresses you send from.

Payload format

The body is one JSON object with a `points` array: one entry per position, one or more vehicles per request.

```
{
  "points": [
    {
      "deviceId": "358480082479488",
      "recordedAt": "2026-10-20T04:12:05Z",
      "lat": 23.0461283,
      "lng": 72.5374399,
      "speedKmh": 32.5,
      "heading": 304,
      "ignition": true,
      "odometerKm": 18342.7
    }
  ]
}
```

Field	Type	Required	Meaning	Your Pull API field
`deviceId`	string	Yes	Tracker IMEI	`Imeino`
`recordedAt`	string, ISO 8601 in UTC (`Z`)	Yes	Time the tracker took the GPS fix	`GPSActualTime`, converted from IST
`lat`	number, decimal degrees	Yes	Latitude, −90 to 90	`Latitude`
`lng`	number, decimal degrees	Yes	Longitude, −180 to 180	`Longitude`
`speedKmh`	number ⩾ 0	Recommended	Speed in km/h	`Speed`
`heading`	number, 0 to 360	Recommended	Direction of travel in degrees, 0 = north	`Angle`
`ignition`	boolean	Recommended	Ignition on (`true`) or off	`IGN`
`odometerKm`	number ⩾ 0	Optional	Odometer in kilometres	`Odometer` (please confirm its unit)

- Numbers as JSON numbers, not strings. Leave a field out when unknown; don't send `"--"`, `0,0` or `null` positions.
- Send only positions with a valid GPS fix.
- Any other field is refused (`400`), so please send only the fields above.

Responses and retries

A `200` means the batch was received; retry anything else except `400` and `401`.

```
{ "accepted": 1, "duplicates": 0, "rejected": 0, "unknownDevices": [] }
```

Status	Meaning	What to do
`200`	Received. Counts show what was stored	Nothing. `unknownDevices` lists IMEIs not registered in PrismGo

Status	Meaning	What to do
`400`	Body not in the format above	Don't retry; fix the payload. The response says which field
`401`	Missing or wrong `X-GPS-Secret`	Don't retry; check the secret
`429`, `5xx`, timeout	Temporary problem on our side	Retry with backoff: 10 s, 30 s, 1 min, 5 min, then every 5 min for up to 24 hours

- Resending a position is safe. Each vehicle stores one position per `recordedAt`, so duplicates are counted, not stored twice.
- After an outage, please send the queued positions oldest first. We accept positions up to 7 days old.
- Positions more than 2 minutes in the future are rejected, so keep server clocks synchronised (NTP).
- Use a timeout of at least 10 seconds on your side; we normally answer in under 1 second.

Frequency and limits

Push each position as it arrives from the tracker, at least every 15 seconds while a vehicle is moving.

Item	Value
Moving vehicle	Every position, at least one every 10–15 seconds
Stopped or ignition off	One every 1–5 minutes is enough
Batching	Several positions and vehicles per request are fine; up to 1,000 points per request
Order	Oldest first within a request
Fleet at launch	About 2–10 vehicles; please plan for growth to a few hundred

Device mapping and testing

Positions are matched to vehicles by IMEI, so please send us the IMEI and registration number of every tracker on the client's account. We register them in PrismGo before testing.

1. We send the shared secret separately (not by email).
2. You send a test batch for one vehicle. We confirm a `200` with `accepted` ⩾ 1 and the vehicle on our live map.
3. You switch on push for all of the client's vehicles. We run both push and pull for one day and compare.
4. We switch off polling of the Pull API.

Open questions:

- [ ] Unit of the `Odometer` field (metres or kilometres).
- [ ] IP addresses you send from, if firewall rules are needed.
- [ ] Your support contact during integration testing.

BlackPrism contact: Sandeep, sandeep@blackprism.in (copy admin@blackprism.in).