



What is a discount rate?

Cliff Ang Vice President, Compass Lexecon

Capital Asset Pricing Model (CAPM)

Mathematically, the CAPM is as follows:

$$E(R_i) = R_f + \beta_i (R_m - R_f)$$

where

- $E(R_i)$ is the return on stock i
- R_f is the risk-free rate of return
- R_m is the market return
- $R_m R_f$ is the equity risk premium (ERP)
- β_i is the sensitivity of stock i's return to the market return



Beta

- Don't put your eggs in one basket
- You should always try to reduce firm-specific risk
- Investors are only compensated from taking on systematic risk (a/k/a market or undiversifiable risk)
- Beta is a measure of *systematic risk*

Using Regression Analysis to Estimate Beta

Beta is typically estimated using a market model regression of the form:

$$R_i = \alpha + \beta \times R_m$$

(no risk-free rate!!!)

where

- α and β are coefficients generated by the regression
- R_i is the return on stock i
- R_m is the market return



Using Regression Analysis to Estimate Beta

The regression is typically performed using

- 2 to 5 year estimation period
- Weekly or monthly returns

Estimating Beta

```
> # Calculate stock return
> rets <- Delt(prices$firm ret)</pre>
> # Calculate market return
> rets$spy <- Delt(prices$spy)</pre>
> # Rename first variable
> names(rets)[1] <- "firm ret"</pre>
> # Remove first observation - NA
> rets <- rets[-1, ]
> # Run regression
> reg <- lm(myl ~ spy, data = rets)</pre>
> # Extract beta
> beta <- summary(reg)$coeff[2]</pre>
```





Let's practice!





Unlevering Betas

Cliff Ang

Vice President, Compass Lexecon

The Hamada Formula

Unlevering Beta using Hamada Formula:

$$eta_U = eta_L/(1+(1-T_c) imes D/E)$$

where

- β_U is the Unlevered Beta (beta without effects of leverage)
- β_L is the Levered or Equity Beta (beta from regression)
- T_c is the corporate tax rate
- D/E is the debt-to-equity ratio

Relevering Beta Using Hamada Formula:

$$eta_L = eta_U imes (1 + (1 - T_c) imes D/E)$$

Fernandez Formula

Unlevering Beta using Fernandez Formula:

$$eta_U = [eta_L + eta_D (1 - T_c) D/E]/[1 + (1 - T_c) D/E]$$

Same variable definitions as Hamada Formula, except for the addition of β_D for the debt beta.

Relevering Beta Using Fernandez Formula:

$$eta_L = eta_U + (eta_U - eta_D)(1 - T_c)D/E$$

Hamada Formula = Fernandez Formula if $\beta_D=0$

Betas Used in Valuation

Which betas do you use in the CAPM?

- Use the beta obtained form regressing the stock's return on the market's return
- Use the relevered beta based on the median or average peer company's unlevered beta





Let's practice!





Risk-Free Rate and Equity Risk Premium

Cliff Ang Vice President, Compass Lexecon

Risk-Free Rate

• A risk-free security is an asset with a beta of zero (i.e., no systematic risk)

```
If eta_i=0, then R_i=R_f+eta_i(R_m-R_f)\Rightarrow R_i=R_f
```

- Yield on US Treasury securities is often used as proxy for risk-free rate
- Use a long-term US Treasury security (i.e., 10, 20, or 30 years)
- We can obtain the data from the Federal Reserve Electronic Database or the Federal Reserve H.15 Selected Interest Rates Database

Equity Risk Premium

- Equity Risk Premium (ERP) is the extra return that investors demand for putting their money in stocks, as proxied by the S&P 500, instead of Treasuries
- ullet Mathematically, $ERP=R_m-R_f$
- The ERP can be different depending on the term of the risk-free rate used but **consistency is key**
 - For example, if R_f in the CAPM is based on 10-year Treasuries, then ERP should be calculated using 10-year Treasuries
- ERP is the average annual R_m-R_f over a period of **at least 35 years**
- The typical range for the FRP is 5% to 8%





Let's practice!