
Table Of Content:

- Getting Started
- Bolts Comment Attribute
- Bolts Input Action Attribute
- Bolts Animation Clip Attribute
- Bolts Animation Parameter Attribute
- Bolts Tool Tip Attribute
- Bolts Shader Property Attribute
- Bolts Static Viewer Attribute
- Bolts Saving Tool
- Bolts Debug Window
- Bolts Commands
- Bolts Timer
- Bolts Notes



Small Tools:

- Grid Spawner
- Screenshot
- Make SO
- Select All With Component
- Batch Renamer
- Bolts Edit ScriptableObjects

Custom Components:

- Bolts Box Collider
- Bolts Material Instance Editor
- Bolts World Transform



Getting Started:

To Start, Download And Import Bolts Tools.


Recommended Assets: DoTween And NaughtyAttributes

Bolts Comment Attribute:

Type [BoltsCommentAttribute(Comment, Space)] Over A Variable You Want To Have A Comment. Does Not Work On Lists.

Comment = The String You Want To Be A Comment.

Space = The Space After The Comment. If Left Empty, It Will Be 10.



Bolts Input Action Attribute:

BoltsInputActionAttribute Is Used To Get A InputActionMap As A String In A Dropdown In The Inspector.

Type [BoltsInputAction(ActionAsset)] Above A String Variable.

ActionAsset = The Name Of The InputActionAsset Variable You Want To Get The InputActionMap From.

Bolts Animation Clip Attribute:

Type [BoltsAnimationClip(Animator)] Over A String To Get A Drop Down Of All Animation Clips.

Animator = The Name Of The Animator/Controller


Bolts Animation Parameter Attribute:

Type [BoltsAnimationParam(Animator)] Over A String To Get A Drop Down Of All The Parameters.

Animator = The Name Of The Animator/Controller

Bolts Tool Tip Attribute:

Type [BoltsToolTip(msg)] Above A Variable You Want To Have A Tool Tip.
msg = The String You Want To Show When Hovering Above The Variable.



Bolts Shader Property Attribute:

BoltsShaderPropertyAttribute Is Used To Get A Shader Property As A String In A Dropdown In The Inspector. Also Works On Shader Graph

Type [BoltsShaderProperty(Material)] Above A String Variable.

Material = The Material Variable Name To Get The Property From

Bolts Static Viewer Attribute

BoltsStaticViewerAttribute Is Used To Show A Static Variable In The Inspector.

Type [BoltsStaticViewer(Editable = bool)] Above A Variable.

Editable = bool = If The Static Variable Should Be Editable In The Inspector Or Not.
The Editable = bool Can Be Removed.

Bolts Saving Tool:

Type BoltSave.SaveType(Name, Value); To Save A Value.

Type BoltSave.GetType(Name); To Get A Saved Value.


Name = Name Of The Variable (Could Be Anything As Long As It Is A String).
Value = The Value Of The Variable You Wanna Save.

Save Type:		
SaveFloatValue	=======	Saves A Float
SaveIntValue	=======	Saves An Int
SaveStringValue	=======	Saves A String
SaveBoolValue	=======	Saves A Bool
SaveClassValue	=======	Saves A Class

Get Type:		
GetFloat	=======	Returns A Saved Float
GetInt	=======	Returns A Saved Int
GetString	=======	Returns A Saved String
GetBool	=======	Returns A Saved Bool
LoadClass	=======	Returns A Saved Class

Type [BoltsSave(SavedVariableType.Type, saveIndex)] Above A string Variable To Get A Dropdown Of All Saved Variables.

SavedVariableType.Type = Any, Float, Int, String, Bool, Class.
SaveIndex = The Index Of The Save File, Can Be Left Empty.




Save File Name = The Name Of The Save File.
If You Want It In A Folder, Then Set It To FolderName/FileName.json.


Use Persistent Data Path = Use The C:\User*UserName*\AppData\LocalLow\CompanyName\ProjectName.

Use Encryption = Do You Want To Encrypt The Data In The File. (Note, The Encryption Is Not Strong, It's Just There To Make It Harder To Read The File).
Save File = The Save File You Want To Add Default Values To.
If You Want To Add More Save Files, Go To Assets/Resources/SaveSettings.


Reload JSON = Reloads The Save File.



Show Saved Data = Shows You All Your Saved Variables Like This:



Save Type = The Type You Want To Have A Default Value.
Value Name = The Name Of The Saved Variable.
Saved X = The Value Of The Variable.



Bolts Debug Window:

Type BoltsDebugMenu.AddLog(logString, stackTrace, type); To Add A Log

LogString = The String In The Log.

stackTrace = Where The Call Came From.

type = What Type Of Log It Is.

Key To Open = The Key To Open The Debug Menu.

Show FPS = Show FPS In Debug Menu.

Show Player Position = Show The Players Position In The Debug Menu.

Save Log = Whether To Save Logs Or Not.

Unlocked Cursor = When Typing A Command, Should The Cursor Be Unlocked?


Key To Open Commands = The Key To Open The Commands Menu.

Show Debug = Show The Debug Screen When Clicking On Key To Open.

Show Commands = Show The Command Window When Clicking On Key To Open Commands.

Change Path = Change The Path Of The Logs.

Player Tag = The Players Tag, Can Only Be On Game Object With That Tag.



Bolts Commands:

Type BoltsCommands.AddCommand(commandName, methodName, target, description); To Add A Command.
Or You Could Type BoltsCommands.AddCommand(commandName, action, description);

commandName = What You Type To Call The Command.
methodName = The Name Of The Method The Command Should Call. Don't Add Arguments, Add Them When Typing The Command.

action = The Action You Want The Command To Do.
target = The MonoBehaviour Script That Should Run The Command.
description = The Description Of The Command. (Can be Left Empty).

Type BoltsCommands.RemoveCommand(commandName); To Remove A Command
commandName = The Name Of The Command You Want To Remove

To Run A Command, Press keyToOpenCommands, Then Type The Command Name And The Arguments If It Has Arguments.

Bolts Timer:

Type StartCoroutine(BoltsTimer.FreezeFrame(sec)); To Add Freeze Frames.
sec = The Number Of Seconds The Frame Is Frozen.

Type StartCoroutine(BoltsTimer.WaitFor(T, F)); To Do An Action When Condition Is True.
T = The Condition(s).
F = The Action To Run.

Type StartCoroutine(BoltsTimer.WaitForSeconds(sec, F)); To Do An Action After An Amount Of Seconds.
sec = The Seconds To Wait.
F = The Action To Run.

Type StartCoroutine(BoltsTimer.WaitForAnimation(animator, clipName, F)); To Run An Action After An Animation Is Done Playing.
animator = The Animator That Is Playing The Animation.
clipName = The Name Of The Animation Clip.
F = The Action To Run.

Type BoltsTimer.FreezeGame(); To Freeze The Game.


Type StartCoroutine(BoltsTimer.FrameStep(frames)); To Step Frames.
frames = The Number Of Frames To Step.

Type StartCoroutine(BoltsTimer.HoldInput(condition, frames, toDo)); To For X Frames And Checks If A Condition Is True And Then Run An Action.
condition = The Condition For The Action To Run.
frames = Max Frames To Wait.
toDo = The Action To Run.


Bolts Notes:

To Start, Go To Tools/Bolts Tools/Notes, Or Press Alt + N.

Right Click And Click Create Sticky Note To Add A Note.



Clicking On Sticky Note Makes It So You Can Re Name It.



Having 2 Notes Makes It So You Can Draw A Line Between Them.



Small Tools:


Grid Spawner:

Spawn Multiple = Spawn More Than One Object
Prefab = The Prefab You Want To Spawn In A Grid
Parent = The Parent Object Of The Spawned Objects (Can Be Empty)
Grid Size = How Many In Each Direction You Want To Spawn
Start Position = The Center Of The First Object To Spawn
Rotation = The Rotation You Want For Each Object
Offset = The Distends Between The Center Of All Objects
Hide Preview Position = Hide The Start Preview Position
Preview = Preview The Grid
Spawn Grid = Spawns The Grid




Screenshot:

File Name = The File Name Of The Image
Set Path = Set The Path Of The Image. Default Is In Assets
Take Screenshot = Takes The Screenshot



Make SO:


Type = The ScriptableObject Script
Asset Name = The Name Of The ScriptableObject Asset
Create Scriptable Object = Creates The ScriptableObject




s

Select All With Component:

Select With Name = Select Game Objects By Name
Component Type = The Component On All Game Objects You Want To Select
Re-scan Scene = Re-scan The Scene




Name = The Name Of All Game Objects You Want To Select




Batch Renamer:

Objects Names = The New Name Each Selected Game Object Will Get
Add Index To Name = Names Will Be "Objects Names (1)", "Objects Names (2)" etc.



Bolts Edit ScriptableObjects:

Select ScriptableObject = The ScriptableObject You Want To Edit.
Ping Object = Ping The Object In The Project Window.




Custom Components:

Bolts Box Collider:

Is A Normal Box Collider With One Thing Added

+-X, +-Y, +-Z = What Direction To Stretch In Local
Set Bounds = Stretches The Bounds In The Chosen Directions To The Closes Collider



Bolts Material Instance Editor:

Makes It So You Can Edit A Material On A Game Object Without Changing The Original.

Not Recommended To Use For Build Games, Only For Place Holder.

Bolts World Transform:

Makes It So You Can Edit The World Transform Of A Child In The Inspector.