RH133 - Red Hat Linux System Administration

Introduction - RH133 Red Hat Enterprise Linux Administration

Copyright

Welcome

Participant Introductions

Red Hat Enterprise Linux

Red Hat Enterprise Linux Variants

Red Hat Network

Other Red Hat Supported Software

Notes on Internationalization

The Fedora Project

Classroom Network

<u>Objectives</u>

Audience and Prerequisites

Unit 1 - System Initialization

Objectives

Boot Sequence Overview

Boot Loader Components

GRUB and grub.conf

Starting the Boot Process: GRUB

Kernel Initialization

init Initialization

Run Levels

/etc/rc.d/rc.sysinit

/etc/rc.d/rc

System V run levels

/etc/rc.d/rc.local

Controlling Services

End of Unit 1

Unit 2 - Package Management

Objectives

RPM Package Manager

Installing and Removing Software

Updating a Kernel RPM

rpm Queries

rpm Verification

About yum

Using yum

Searching packages/files

Configuring Additional Repositories

Creating a private repository

Red Hat Network

Red Hat Network Server

Entitlements

Red Hat Network Client

End of Unit 2

Unit 3 - Kernel Services

Objectives

The Linux Kernel

Kernel Images and Variants

Kernel Modules

Kernel Module Utilities

Managing the initrd Image

RH133 - Red Hat Linux System Administration
Accessing Drivers Through /dev
Device Node Examples
Managing /dev With udev
Adding Files Under /dev
Kernel Configuration With /proc
/proc Examples
sysctl: Persistent Kernel Configuration
Exploring Hardware Devices
Monitoring Processes and Resources
Unit 4 - System Services
<u>Sint i Sjotom Gortioss</u>
<u>Objectives</u>
Network Time Protocol
System Logging
syslog Configuration
XOrg: The X11 Server
XOrg Server Configuration
XOrg in runlevel 3
XOrg in runlevel 5
Remote X Sessions
SSH: Secure Shell
VNC: Virtual Network Computing
cron
Controlling Access to cron
System crontab Files

Daily Cron Jobs

End of Unit 4

<u>CUPS</u>

The anacron System

Unit 5 - User Administration

Objectives

Adding a New User Account

User Private Groups

Modifying / Deleting User Accounts

Group Administration

Password Aging Policies

Switching Accounts

<u>sudo</u>

Network Users

Authentication Configuration

Example: NIS Configuration

Example: LDAP Configuration

SUID and SGID Executables

SGID Directories

The Sticky Bit

Default File Permissions

Access Control Lists (ACLs)

SELinux

SELinux, continued

SELinux: Targeted Policy

SELinux: Management

End of Unit 5

Unit 6 - Filesystem Management

Objectives

Overview: Adding New Filesystems to the Filesystem Tree

Device Recognition

Disk Partitioning

Managing Partitions

RH133 - Red Hat Linux System Administration
Making Filesystems
<u>Filesystem Labels</u>
<u>tune2fs</u>
Mount Points and /etc/fstab
Mounting Filesystems with mount
<u>Unmounting Filesystems</u>
mount By Example
Handling Swap Files and Partitions
Mounting NFS Filesystems
<u>Automounter</u>
<u>Direct Maps</u>
anome-mount
gnome-mount
End of Unit 6
End of Unit 6
End of Unit 6 Unit 7 - Advanced Filesystem Management
End of Unit 6 Unit 7 - Advanced Filesystem Management Objectives
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID?
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID? Software RAID Configuration
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID? Software RAID Configuration Software RAID Testing and Recovery
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID? Software RAID Configuration Software RAID Testing and Recovery What is Logical Volume Manager (LVM)?
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID? Software RAID Configuration Software RAID Testing and Recovery What is Logical Volume Manager (LVM)? Creating Logical Volumes
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID? Software RAID Configuration Software RAID Testing and Recovery What is Logical Volume Manager (LVM)? Creating Logical Volumes Resizing Logical Volumes
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID? Software RAID Configuration Software RAID Testing and Recovery What is Logical Volume Manager (LVM)? Creating Logical Volumes Resizing Logical Volumes Logical Volume Manager Snapshots
Unit 7 - Advanced Filesystem Management Objectives Configuring the Quota System Setting Quotas for Users Reporting Quota Status What is Software RAID? Software RAID Configuration Software RAID Testing and Recovery What is Logical Volume Manager (LVM)? Creating Logical Volumes Resizing Logical Volumes Logical Volume Manager Snapshots Using LVM Snapshots
Unit 7 - Advanced Filesystem Management Objectives Configuring the Ouota System Setting Ouotas for Users Reporting Ouota Status What is Software RAID? Software RAID Configuration Software RAID Testing and Recovery What is Logical Volume Manager (LVM)? Creating Logical Volumes Resizing Logical Volumes Logical Volume Manager Snapshots Using LVM Snapshots Archiving tools: tar

Unit 8 - Network Configuration

Objectives

Network Inferfaces

Driver Selection

Speed and Duplex Settings

IPv4 Addresses

Dynamic IPv4 Configuration

Static IPv4 Configuration

Device Aliases

Routing Table

Default Gateway

Configuring Routes

Verify IP Connectivity

Defining the Local Host Name

Local Resolver

Remote Resolvers

Verify DNS Connectivity

Network Configuration Utilities

Transparent Dynamic Configuration

Implementing IPv6

IPv6: Dynamic Interface Configuration

IPv6: StaticInterface Configuration

IPv6: Routing Configuration

New and Modified Utilities

End of Unit 8

Unit 9 - Installation

Objectives

Anaconda, the Red Hat Enterprise Linux Installer

RH133 - Red Hat Linux System Administration

First Stage: Starting the Installation

First Stage: Boot Media

Accessing the Installer

First Stage: Installation Method

Network Installation Server

Second Stage: Installation Overview

Configuring File Systems

Advanced Partitioning

Package Selection

First Boot: Post-Install Configuration

Kickstart

Starting a Kickstart Installation

Anatomy of a Kickstart File

Kickstart: Commands Section

Kickstart: Commands section

Kickstart: Packages Section

Kickstart: %pre, %post

End of Unit 9

Unit 10 - Virtualization with Xen

Objectives

Virtualization with Xen

Hardware Considerations

Preparing Domain-0

Virtual Resources

Domain-U Configuration

Installing a new Domain-U

Domain Management with xm

Activating Domains on boot

End of Unit 10

Unit 11 - Troubleshooting

Objectives

Method of Fault Analysis

Fault Analysis: Gathering Data

Things to Check: X

Things to Check: Networking

Order of the Boot Process

Filesystem Corruption

Filesystem Recovery

Recovery Run-levels

Rescue Environment

Rescue Environment Utilities

Rescue Environment Details

End of Unit 11



RH133 Red Hat Enterprise Linux Administration

RH133-RH133-RHEL5-en-1-20070321





Copyright

- The contents of this course and all its modules and related materials, including handouts to audience members, are Copyright © 2007 Red Hat, Inc.
- No part of this publication may be stored in a retrieval system, transmitted or reproduced in any way, including, but not limited to, photocopy, photograph, magnetic, electronic or other record, without the prior written permission of Red Hat, Inc.
- This instructional program, including all material provided herein, is supplied without any guarantees from Red Hat, Inc. Red Hat, Inc. assumes no liability for damages or legal action arising from the use or misuse of contents or details contained herein.
- If you believe Red Hat training materials are being used, copied, or otherwise improperly distributed please email training@redhat.com or phone toll-free (USA) +1 866 626 2994 or +1 919 754 3700.

RH133-RH133-RHEL5-en-1-20070321





Welcome

Please let us know if you have any special needs while at our training facility.

RH133-RH133-RHEL5-en-1-20070321





Participant Introductions

Please introduce yourself to the rest of the class!

RH133-RH133-RHEL5-en-1-20070321





Red Hat Enterprise Linux

- Enterprise-targeted operating system
- Focused on mature open source technology
- 18-24 month release cycle
 - Certified with leading OEM and ISV products
- Purchased with one year Red Hat Network subscription and support contract
 - Support available for seven years after release
 - Up to 24x7 coverage plans available

RH133-RH133-RHEL5-en-1-20070321





Red Hat Enterprise Linux Variants

- Two Install Sets available
- Server Spin
 - Red Hat Enterprise Linux
 - Red Hat Enterprise Linux Advanced Platform
- · Client Spin
 - Red Hat Enterprise Linux Desktop
 - Workstation Option
 - Multi-OS Option

RH133-RH133-RHEL5-en-1-20070321





Red Hat Network

- A comprehensive software delivery, system management, and monitoring framework
 - Update Module
 Provides software updates
 - Included with all Red Hat Enterprise Linux subscriptions
 - Management
 Module : Extended capabilities for large deployments
 - Provisioning
 Module : Bare-metal installation,
 configuration management, and multi-state
 configuration rollback capabilities
 - Monitoring
 Module
 provides infrastructure health monitoring of networks, systems, applications, etc.

RH133-RH133-RHEL5-en-1-20070321





Other Red Hat Supported Software

- Global Filesystem
- Directory Server
- Certificate Server
- Red Hat Application Stack
- JBoss Middleware Application Suite

RH133-RH133-RHEL5-en-1-20070321





Notes on Internationalization

- Red Hat Enterprise Linux supports nineteen languages
- Default language can be selected:
 - During installation
 - With system-config-language
 - System->Administration->Language
- Alternate languages can be used on a percommand basis:
- \$ LANG=en US.UTF8 date
- Language settings are stored in /etc/ sysconfig/i18n

RH133-RH133-RHEL5-en-1-20070321





The Fedora Project

- Red Hat sponsored open source project
- Focused on latest open source technology
 - o Rapid four to six month release cycle
 - Available as free download from the Internet
- An open, community-supported proving ground for technologies which may be used in upcoming enterprise products
- Red Hat does not provide formal support

RH133-RH133-RHEL5-en-1-20070321





Classroom Network

	Names	IP Addresses
Our Network	example.com	192.168.0.0/24
Our Server	server1.example.com	192.168.0.254
Our Stations	stationx.example.com	192.168.0. <i>x</i>
Hostile Network	cracker.org	192.168.1.0/24
Hostile Server	server1.cracker.org	192.168.1.254
Hostile Stations	stationx.cracker.org	192.168.1. <i>x</i>
Trusted Station	trusted.cracker.org	192.168.1.21

RH133-RH133-RHEL5-en-1-20070321





Objectives

- Understand system and service initialization
- Integrate new filesystems
- Understand advanced partitioning schemes
- Perform filesystem management tasks
- Set up networking
- Perform user and group administration
- Automate tasks with at, cron, and anacron
- Set up core services: Logging, Printing, X
 Window system
- Manage software packages with yum and rpm
- Install the system interactively and with Kickstart
- Perform basic troubleshooting

RH133-RH133-RHEL5-en-1-20070321





Audience and Prerequisites

- Audience: Linux or UNIX users, who understand the basics of Red Hat Linux, that desire further technical training to begin the process of becoming a system administrator.
- Prerequisites: RH033 Red Hat Linux Essentials or equivalent experience with Red Hat Enterprise Linux.

RH133-RH133-RHEL5-en-1-20070321





Unit 1

System Initialization

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Discuss the boot sequence
- Understand GRUB's role
- Understand init's role
- Control System V services

RH133-RH133-RHEL5-en-1-20070321





Boot Sequence Overview

- BIOS Initialization
- Boot Loader
- Kernel initialization
- init starts and enters desired run level by executing:
 - o /etc/rc.d/rc.sysinit
 - o /etc/rc.d/rc and /etc/rc.d/rc?.d/
 - o /etc/rc.d/rc.local
 - X Display Manager if appropriate

RH133-RH133-RHEL5-en-1-20070321





Boot Loader Components

- Boot Loader
 - 1st Stage small, resides in MBR or boot sector
 - 2nd Stage loaded from boot partition
- Minimum specifications for Linux:
 - Label, kernel location, OS root filesystem and location of the initial ramdisk (initrd)
- Minimum specification for other OS:
 - o boot device, label

RH133-RH133-RHEL5-en-1-20070321





GRUB and grub.conf

- GRUB "the GRand Unified Bootloader"
 - o Command-line interface available at boot prompt
 - Boot from ext2/ext3, ReiserFS, JFS, FAT, minix, or FFS file systems
 - Supports MD5 password protection
- /boot/grub/grub.conf
- Changes to grub.conf take effect immediately
- If MBR on /dev/hda is corrupted, reinstall the first stage bootloader with:
 - o /sbin/grub-install /dev/hda

RH133-RH133-RHEL5-en-1-20070321





Starting the Boot Process: GRUB

- Image selection
 - Select with space followed by up/down arrows on the boot splash screen
- Argument passing
 - o Change an existing stanza in menu editing mode
 - Issue boot commands interactively on the GRUB command line

RH133-RH133-RHEL5-en-1-20070321





Kernel Initialization

- Kernel boot time functions
 - Device detection
 - Device driver initialization
 - Mounts root filesystem read only
 - Loads initial process (init)

RH133-RH133-RHEL5-en-1-20070321





init Initialization

- init reads its config: /etc/inittab
 - o initial run level
 - o system initialization scripts
 - o run level specific script directories
 - trap certain key sequences
 - o define UPS power fail / restore scripts
 - spawn gettys on virtual consoles
 - o initialize X in run level 5

RH133-RH133-RHEL5-en-1-20070321





Run Levels

- init defines run levels 0-6, S, emergency
- The run level is selected by either
 - o the default in /etc/inittab at boot
 - o passing an argument from the boot loader
 - using the command init new_runlevel
- Show current and previous run levels
 - o /sbin/runlevel

RH133-RH133-RHEL5-en-1-20070321





/etc/rc.d/rc.sysinit

- Important tasks include:
 - Activate udev and selinux
 - Sets kernel parameters in /etc/sysctl.conf
 - Sets the system clock
 - Loads keymaps
 - Enables swap partitions
 - Sets hostname
 - Root filesystem check and remount
 - Activate RAID and LVM devices
 - Enable disk quotas
 - Check and mount other filesystems
 - Cleans up stale locks and PID files

RH133-RH133-RHEL5-en-1-20070321





/etc/rc.d/rc

 Initializes the default run level per the /etc/ inittab file initdefault line such as id:3:initdefault:

```
• 10:0:wait:/etc/rc.d/rc 0
11:1:wait:/etc/rc.d/rc 1
12:2:wait:/etc/rc.d/rc 2
13:3:wait:/etc/rc.d/rc 3 (default)
14:4:wait:/etc/rc.d/rc 4
15:5:wait:/etc/rc.d/rc 5
16:6:wait:/etc/rc.d/rc 6
```

RH133-RH133-RHEL5-en-1-20070321





System V run levels

- Run level defines which services to start
 - Each run level has a corresponding directory:
 - /etc/rc.d/rcX.d
 - o The System V init scripts reside in:
 - /etc/rc.d/init.d
 - Symbolic links in the run level directories call the init.d scripts with a start or stop argument

RH133-RH133-RHEL5-en-1-20070321





/etc/rc.d/rc.local

- Run after the run level specific scripts
- Common place for custom modification
- In most cases it is recommended that you create a System V init script in
- /etc/rc.d/init.d unless the service you are starting is so trivial it doesn't warrant it.
 Existing scripts can be used as a starting point.

RH133-RH133-RHEL5-en-1-20070321





Controlling Services

- Utilities to control default service startup
 - system-config-services: graphical utility that requires an X interface
 - ntsysv: ncurses based utility usable in virtual consoles
 - chkconfig: a fast, versatile command line utility that works well and is usable with scripts and Kickstart installations
- Utilities to control services manually
 - service: immediately start or stop a standalone service
 - chkconfig immediately starts and stops xinetdmanaged services

RH133-RH133-RHEL5-en-1-20070321





End of Unit 1

- Questions and Answers
- Summary
 - System BIOS
 - o GRUB
 - init
 - o chkconfig and service

RH133-RH133-RHEL5-en-1-20070321





Package Management

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Install and remove RPM packages
- Query packages and verify their state
- Manage packages using yum
- Understand the relationship between yum and rpm
- Configure yum to connect to a RHN Satellite Server
- Create a private yum repository
- Configure yum to connect to a private repository
- Configure and use Red Hat Network

RH133-RH133-RHEL5-en-1-20070321





RPM Package Manager

- RPM Components
 - local database
 - o **rpm** and related executables
 - RPM frontends such as yum
 - o package files
- Primary Functions
 - install/remove
 - o query
 - o verify

RH133-RH133-RHEL5-en-1-20070321





Installing and Removing Software

• Primary RPM options:

o Install: rpm -i, --install

Upgrade: rpm -U, --upgrade

o Freshen: rpm -F, --freshen

o Erase: rpm -e, --erase

Output Options: -v, -h

URL support: ftp:// (with globbing),

http://

 Many other install-options are available to address special cases.

RH133-RH133-RHEL5-en-1-20070321





Updating a Kernel RPM

- Make sure to install kernel updates
- Do not use rpm -U or rpm -F!
 - o rpm -ivh kernel-version.arch.rpm
 - Boot new kernel to test
 - Revert to old kernel if a problem arises
 - o rpm -e kernel-oldversion if no problems

RH133-RH133-RHEL5-en-1-20070321





rpm Queries

- Syntax:
 - rpm -q what_packages what_information
- Installed Package Options:
 - o rpm -qa lists installed packages
 - o rpm -qf filename shows owning package
 - o rpm -qi package_name general information
 - o rpm -ql package_name lists files in package
- Uninstalled Package Options:
 - o rpm -qip package_file.i386.rpm
 - rpm -qlp package_file.i686.rpm

RH133-RH133-RHEL5-en-1-20070321





rpm Verification

- Installed RPM File Verification:
 - o rpm -V <package_name>
 - o rpm -Vp <package_file>.i386.rpm
 - o rpm -Va
- Signature verification BEFORE package install:
 - o rpm --import RPM-GPG-KEY
 - o rpm -K <package_file>.i386.rpm

RH133-RH133-RHEL5-en-1-20070321





About yum

- Front-end to rpm
 - Designed to resolve package dependencies
 - Can locate packages across multiple repositories
- Replacement for up2date

RH133-RH133-RHEL5-en-1-20070321





Using yum

- Install/Remove/Update
 - o **yum install** package...
 - o **yum remove** package...
 - o yum update [package...]

RH133-RH133-RHEL5-en-1-20070321





Searching packages/files

- Searching packages
 - o **yum search** searchterm
 - o yum list (all/available/extras/installed/ recent/updates)
 - o **yum info** packagename
- Searching files
 - o yum whatprovides filename

RH133-RH133-RHEL5-en-1-20070321





Configuring Additional Repositories

- Create a file in /etc/yum.repos.d for your repository
- Required information
 - o [repo-name]
 - o name=A nice description
 - o baseurl=http://yourserver.com/path/to/
 repo
 - o enabled=1
 - o gpgcheck=1

RH133-RH133-RHEL5-en-1-20070321





Creating a private repository

- Create a directory to hold your packages
- Make this directory available by http/ftp
- Install the createrepo RPM
- Run createrepo -v /package/directory
- This will create a repodata subdirectory and the needed support files

RH133-RH133-RHEL5-en-1-20070321





Red Hat Network

- Centralized platform for systems mangement
 - o provides Red Hat software packages
 - o shows if errata are available for systems
 - o can update many systems at once
 - o allows full life cycle management
- Webbased management interface
- Uses HTTPS for all transactions

RH133-RH133-RHEL5-en-1-20070321





Red Hat Network Server

- rhn.redhat.com or local Satellite/Proxy
 - Web based management of machines
 - RHN Proxy caches RHN traffic
 - RHN Satellite provides an autonomous RHN
- RHN Accounts
 - RHN Users for registration of machines and web based management
 - System ID for automatic authentication of systems

RH133-RH133-RHEL5-en-1-20070321





Entitlements

- Grant access to software channels
 - Base Channel
 - o Child Channel(s)
- Define level of service
 - Update
 - Management
 - o Provisioning
 - Monitoring

RH133-RH133-RHEL5-en-1-20070321





Red Hat Network Client

- Registration
 - Run rhn_register
 - Select the updates location (RHN or local satellite/ proxy)
 - Enter Account information
- Interactive usage
 - yum plugin for downloading packages from RHN
 - o Configuration in /etc/yum/pluginconf.d/rhnplugin.conf
- Remote management
 - rhnsd polls RHN every four hours
 - o rhn_check polls imediately

RH133-RH133-RHEL5-en-1-20070321





End of Unit 2

- Questions and Answers
- Summary
 - o What are the primary functions of RPM?
 - What **rpm** options should be used to install a kernel RPM?
 - Package-management with yum
 - Relationship between yum and rpm
 - Using yum with RHN
 - Creating a private repository
 - Configuring repositories
 - o How does Red Hat Network work?

RH133-RH133-RHEL5-en-1-20070321





Kernel Services

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Understand the purpose and organization of the kernel
- Understand how to load and configure kernel modules.
- Know how to configure the kernel using / proc and sysctl
- Explore hardware devices available on the system

RH133-RH133-RHEL5-en-1-20070321





The Linux Kernel

- The kernel constitutes the core part of the Linux operating system.
- Kernel duties:
 - System initialization: detects hardware resources and boots up the system.
 - Process scheduling: determines when processes should run and for how long.
 - Memory Management: allocates memory on behalf of running processes.
 - Security: Constantly verifies filesystem permissions,
 SELinux contexts and firewall rules.
 - Provides buffers and caches to speed up hardware access.
 - Implements standard network protocols and filesystem formats.
- Documentation available in the kernel-doc
 RPM package

RH133-RH133-RHEL5-en-1-20070321





Kernel Images and Variants

- Architectures supported: x86, x86_64, IA64/ Itanium, PowerPC64, s390x.
- Three kernel versions available for x86:
 - Regular: one or more processors but 4GB of RAM or less
 - PAE: multiple processors and up to 64G of RAM
 - Xen: needed for virtualization
- Kernels always installed under /boot/ vmlinuz-*

RH133-RH133-RHEL5-en-1-20070321





Kernel Modules

- Modules are small kernel extensions that may be loaded and unloaded at will
- Can implement drivers, filesystems, firewall, and more
- Are located under /lib/modules/
 \$(uname -r)/
- Compiled for a specific kernel version and are provided with the kernel RPM.
- Third party modules may be added

RH133-RH133-RHEL5-en-1-20070321





Kernel Module Utilities

- Ismod provides a list of loaded modules
- modprobe can load and unload modules
- modinfo displays information about any available module
- /etc/modprobe.conf used for module configuration:
 - Parameters to pass to a module whenever it is loaded
 - o Aliases to represent a module name
 - Commands to execute when a module is loaded or unloaded

RH133-RH133-RHEL5-en-1-20070321





Managing the initrd Image

- The initial RAM disk provides modules loaded early in the boot process.
- This file is located under /boot/initrd-\$(uname -r).
 img
- Extra modules sometimes need to be added due to:
 - o New hardware added to the system. i.e. SCSI controller
 - New features needed such as USB devices.
 - Module needs to load automatically at boot time.
- Use **mkinitrd** and the **--with** option to rebuild with an extra module:

```
mkinitrd --with=module_name /boot/initrd-$(uname -r).img \
$(uname -r)
```

RH133-RH133-RHEL5-en-1-20070321





Accessing Drivers Through /dev

- Files under /dev used to access drivers
- Reading from and writing to those files are valid operations:
 - Read from serial port: cat /dev/ttyS0
 - Write to serial port: echo "Message" > /dev/ ttyS0
- Three file attributes determine which driver to access:
 - Device type (character or block)
 - Major number
 - Minor number

RH133-RH133-RHEL5-en-1-20070321





Device Node Examples

Block Devices

- o /dev/hda, /dev/hdc IDE hard disk, CDROM
- o /dev/sda, /dev/sdb SCSI, SATA, or USB Storage
- o /dev/md0, /dev/md1 Software RAID

Character Devices

- o /dev/tty[0-6] virtual consoles
- o /dev/null, /dev/zero software Devices
- o /dev/random, /dev/urandom random Numbers

RH133-RH133-RHEL5-en-1-20070321





Managing /dev With udev

- udev manages files stored under /dev/
- Files only created if corresponding device is plugged in
- Files are automatically removed when device is disconnected
- udev statements under /etc/udev/rules.
 d/ determine:
 - Filenames
 - Permissions
 - Owners and groups
 - o Commands to execute when a new device shows up

RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



3-10



Adding Files Under /dev

- The right way to add a /dev entry involves udev:
 - o Create a new file under /etc/udev/rules.d/
 - Insert a statement such as:

```
KERNEL=="sda", NAME="usbkey" , SYMLINK="usbstorage"
```

- This creates a device file named usbkey and a symlink named usbstorage next time /dev/sda gets plugged.
- Files can be added manually with mknod:

mknod /dev/usbdevice b 8 0

mknod not persistent!

Copyright © 2007 Red Hat, Inc. RH133-RH133-RHEL5-en-1-20070321 All rights reserved





Kernel Configuration With /proc

- /proc used to get or set kernel configuration
- Virtual filesystem: files not stored on hard disk
- Entries not persistent: modifications get reinitialized after a reboot
- Used to display process information, memory resources, hardware devices, kernel memory, etc.
- Can be used to modify network and memory subsystems or modify kernel features
- Modifications apply immediately

RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



2_12



/proc Examples

- Read-only files:
 - o /proc/cpuinfo
 - o /proc/1/*
 - /proc/partitions
 - o /proc/meminfo
- Read-Write entries under /proc/sys/:
 - o /proc/sys/kernel/hostname
 - o /proc/sys/net/ipv4/ip_forward
 - o /proc/sys/vm/drop_caches
 - o /proc/sys/vm/swappiness

RH133-RH133-RHEL5-en-1-20070321





sysctl: Persistent Kernel Configuration

- sysctl adds persistence to /proc/sys settings
- Statements added to /etc/sysctl.conf automatically reflected under /proc after a reboot.
- Configuration maintained or monitored using the sysctl command:
 - List all current settings: sysctl -a
 - Reload settings from sysctl.conf: sysctl-p
 - Set a /proc value dynamically: sysctl -w net.ipv4.ip_forward=1

RH133-RH133-RHEL5-en-1-20070321





Exploring Hardware Devices

- A snapshot of all connected devices is maintained by HAL: Hardware Abstraction Layer
- hal-device lists all devices in text mode.
- hal-device-manager displays all devices on a graphical window.
- **Ispci** and **Isusb** list devices connected to the PCI and USB buses, respectively.
- The /proc and /sys filesystems also contain bus and device specific information.

RH133-RH133-RHEL5-en-1-20070321





Monitoring Processes and Resources

- Information available under /proc/ can be hard to understand.
- Interfaces are available to format the data and make it more accessible:
 - Memory: free, vmstat, swapon -s, pmap
 - o Processes: ps, top, gnome-system-monitor
 - o Kernel state: uname, uptime, tload

RH133-RH133-RHEL5-en-1-20070321





Unit 4

System Services

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Understand the importance of time syncronization
- Configure System Logging
- Setup the X Window System
- remotely administer the system
- Automate tasks with cron
- Configure printing

RH133-RH133-RHEL5-en-1-20070321





Network Time Protocol

- Workstation hardware clocks tend to drift over time without correction
- Many application require accurate timing
- Time synchronization makes system logs easier to analyze
- NTP counters the drift by manipulating the length of a second
- NTP clients should use three time servers
- Config file: /etc/ntp.conf
- Config tool: system-config-date

RH133-RH133-RHEL5-en-1-20070321





System Logging

- Centralized logging daemons: syslogd, klogd
- Log file examples:
 - o /var/log/dmesg: Kernel boot messages
 - var/log/messages: Standard system error messages
 - o /var/log/maillog: Mail system messages
 - var/log/secure: Security, authentication, and xinetd messages
- Application log files and directories also reside in /var/log

RH133-RH133-RHEL5-en-1-20070321





syslog Configuration

- syslog System V initialization script in /etc/ rc.d/init.d controls both the syslogd and the klogd daemons
- /etc/syslog.conf
 - Configures system logging
- /etc/sysconfig/syslog
 - Sets switches used when starting syslogd and klogd from the System V initialization script

RH133-RH133-RHEL5-en-1-20070321





XOrg: The X11 Server

- Foundation for the Red Hat Enterprise Linux graphical user interface(GUI)
- Open Source implementation of X11
- Client / Server Architecture
- Core server with dynamically loaded modules
 - o drivers: ati, nv, mouse, keyboard, etc.
 - o extensions: dri, glx, and extmod
- Font Rendering
 - o Native server: xfs
 - Fontconfig/Xft libraries

RH133-RH133-RHEL5-en-1-20070321





XOrg Server Configuration

- Typically configured after installation
- Post-install configuration:
 - Best results while in runlevel 3!
 - system-config-display
 - options:
 - --noui
 - --reconfig
 - o stored in /etc/X11/xorg.conf

RH133-RH133-RHEL5-en-1-20070321





XOrg in runlevel 3

- Two methods to establish the environment
 - o /usr/X11R6/bin/xinit
 - o /usr/X11R6/bin/startx
- Environment configuration
 - o /etc/X11/xinit/xinitrc and ~/.xinitrc
 - o /etc/X11/xinit/Xclients and ~/.Xclients
 - o /etc/sysconfig/desktop

RH133-RH133-RHEL5-en-1-20070321





XOrg in runlevel 5

- Environment established by /sbin/init
- Environment configuration
 - o /etc/inittab
 - /etc/X11/prefdm
 - o /etc/sysconfig/desktop
 - DESKTOP defines the window manager
 - DISPLAYMANAGER defines the display manager
 - o /etc/X11/xdm/Xsession
 - /etc/X11/xinit/xinitrc.d/*
 - ~/.xsession or ~/.Xclients

RH133-RH133-RHEL5-en-1-20070321





Remote X Sessions

- X protocol communication is unencrypted
- Host-based sessions implemented through the xhost command
- User-based sessions implemented through the Xauthority mechanism
- sshd may automatically install xauth keys on remote machine
 - Tunnels X protocol over secure encrypted ssh connection

RH133-RH133-RHEL5-en-1-20070321





SSH: Secure Shell

- · encrypted remote shell
- frequently used for remote system administration
- can copy files securely
- can execute commands remotely
- # ssh root@host 'ifconfig eth0'
- can tunnel X11 and other TCP based network traffic
- supports key based authentication

RH133-RH133-RHEL5-en-1-20070321





VNC: Virtual Network Computing

- Allows to access or share a complete desktop over the network
- Uses significantly less bandwidth as pure remote X connections
- Server
 - Individual users can start a VNC server with the command: vncserver
 - Runs \$HOME/.vnc/xstartup upon startup
 - Requires a VNC password which should not be identical to the system password
 - Servers can automatically be started via /etc/ init.d/vncserver

Client

- connects to a remote VNC server with vncviewer host:screen
- Unique screen numbers distinguish between multiple VNC servers running on the same host
- supports tunneling through SSH: vncviewer -via user@host localhost:1

RH133-RH133-RHEL5-en-1-20070321





cron

- Used to schedule recurring events
- Use crontab to edit, install, and view job schedules
- Syntax
 - o crontab [-u user] file
 - o crontab [-1|-r|-e]
 - -I lists crontab
 - -r removes crontab
 - -e edits crontab using \$EDITOR

RH133-RH133-RHEL5-en-1-20070321





Controlling Access to cron

- Restrict / allow user access to cron
 - o /etc/cron.allow
 - o /etc/cron.deny
- Contains usernames to allow / deny access

RH133-RH133-RHEL5-en-1-20070321





System crontab Files

- Different format than user crontab files
- Master crontab file /etc/crontab runs executables in
 - o /etc/cron.hourly
 - o /etc/cron.daily
 - o /etc/cron.weekly
 - o /etc/cron.monthly
- /etc/cron.d/ directory contains additional system crontab files

RH133-RH133-RHEL5-en-1-20070321





Daily Cron Jobs

tmpwatch

- Cleans old files in specific directories
- Keeps /tmp from filling up

logrotate

- Keeps log files from getting to large
- o Highly configurable in /etc/logrotate.conf

logwatch

- o provides a summary about system activity
- o reports suspicious messages
- o Configuration file: /etc/log.d/conf/logwatch. conf

RH133-RH133-RHEL5-en-1-20070321





The anacron System

- anacron runs cron jobs that did not run when the computer is down
 - Assumes computers are not up continually
 - Vital for laptops, desktops, workstations, and other systems that are not up continually
 - Useful for servers that need to be taken down temporarily
- Configuration file: /etc/anacrontab
 - Field 1: If the job has not been run in this many days...
 - Field 2: wait this number of minutes after reboot and then run it
 - Field 3: job identifier
 - Field 4: the job to run

RH133-RH133-RHEL5-en-1-20070321





CUPS

- uses the Internet Printing Protocol (IPP)
 - o allows remote browsing of printer queues
 - based on HTTP/1.1
 - Uses PPD files to describe printers
 - Configuration files
 - /etc/cups/cupsd.conf
 - /etc/cups/printers.conf
 - Configuration tools
 - system-config-printer
 - Web based on http://localhost:631
 - Commandline management with **Ipadmin**

RH133-RH133-RHEL5-en-1-20070321





End of Unit 4

- Questions and Answers
- Summary
 - System Logging
 - system-config-display
 - Remote Administration tools: ssh and vnc
 - Task Automation
 - o What are the tools to configure cups?

RH133-RH133-RHEL5-en-1-20070321





Unit 5

User Administration

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Configure user and group accounts
- Modify File ownership and permissions
- Use "Special" permissions SUID / SGID / Sticky
- Configure Network Users with NIS and LDAP
- Set ACLs

RH133-RH133-RHEL5-en-1-20070321





Adding a New User Account

- Most common method is useradd:
 - o useradd [options] username
- Running useradd is equivalent to:
 - o editing /etc/passwd, /etc/shadow, /etc/
 group, /etc/gshadow
 - creating and populating home directory
 - o setting permissions and ownership
- Set account password using passwd
- Accounts may be added in a batch with

newusers

RH133-RH133-RHEL5-en-1-20070321





User Private Groups

- When user accounts are created, a private group is also created with the same name
 - Users are assigned to this private group
 - User's new files affiliated with this group
- Advantage: Prevents new files from belonging to a "public" group
- Disadvantage: May encourage making files "world-accessible"

RH133-RH133-RHEL5-en-1-20070321





Modifying / Deleting User Accounts

- To change fields in a user's /etc/passwd entry you can:
 - Edit the file by hand
 - o Use usermod [options] username
- To remove a user either:
 - o Manually remove the user from /etc/passwd, / etc/shadow, /etc/group, /etc/gshadow, / var/spool/mail, etc.
 - o Use userdel [-r] username

RH133-RH133-RHEL5-en-1-20070321





Group Administration

- Entries added to /etc/group and /etc/gshadow
 - groupadd
 - o groupmod
 - o groupdel

RH133-RH133-RHEL5-en-1-20070321





Password Aging Policies

- By default, passwords do not expire
- Forcing passwords to expire is part of a strong security policy
- Modify default expiration settings in /etc/ login.defs
- To modify password aging for existing users, use the chage command
 - o chage [options] username

RH133-RH133-RHEL5-en-1-20070321





Switching Accounts

- Syntax
 - su [-] [user]
 - o su [-] [user] -c command
- Allows the user to temporarily become another user
 - Default user is root
- The "-" option makes the new shell a login shell

RH133-RH133-RHEL5-en-1-20070321





sudo

- Users listed in /etc/sudoers execute commands with:
 - o an effective user id of 0
 - o group id of root's group
- An administrator will be contacted if a user not listed in /etc/sudoers attempts to use
 sudo

RH133-RH133-RHEL5-en-1-20070321





Network Users

- Information about users may be centrally stored and managed on a remote server
- Two types of information must always be provided for each user account
 - Account information: UID number, default shell, home directory, group memberships, and so on
 - Authentication: a way to tell that the password provided on login for an account is correct

RH133-RH133-RHEL5-en-1-20070321





Authentication Configuration

- system-config-authentication
 - o GUI tool to configure authentication
 - o For text-based tool, use authconfig-tui
 - o Load authconfig-gtk RPM
- Supported account information services:
 - o (local files), NIS, LDAP, Hesiod, Winbind
- Supported authentication mechanisms:
 - o (NSS), Kerberos, LDAP, SmartCard, SMB, Winbind

RH133-RH133-RHEL5-en-1-20070321





Example: NIS Configuration

- Must install ypbind and portmap RPMs
- Run system-config-authentication
 - Enable NIS to provide User Information
 - Specify NIS server and NIS domain name
 - Keep default authentication (through NSS)
- What does this actually do?
 - Five text-based configuration files are changed

RH133-RH133-RHEL5-en-1-20070321





Example: LDAP Configuration

- Must install nss-ldap and openldap RPMs
- Run system-config-authentication
 - Enable LDAP to provide User Information
 - Specify server, the search base DN, and TLS
 - Enable LDAP to provide Authentication
- What does this actually do?
 - Five text-based configuration files are changed

RH133-RH133-RHEL5-en-1-20070321





SUID and SGID Executables

- Normally processes started by a user run under the user and group security context of that user
- SUID and/or SGID bits set on an executable file cause it to run under the user and/or group security context of the file's owner and/or group

RH133-RH133-RHEL5-en-1-20070321





SGID Directories

- Used to create a collaborative directory
- Normally, files created in a directory belong to the user's the default group
- When a file is created in a directory with the SGID bit set, it belongs to the same group as the directory

RH133-RH133-RHEL5-en-1-20070321





The Sticky Bit

- Normally users with write permissions to a directory can delete any file in that directory regardless of that file's permissions or ownership
- With the sticky bit set on a directory, only the owner of a file can delete the file
- Example:

```
ls -ld /tmp
drwxrwxrwt 12 root root 4096 Nov 2 15:44 /tmp
```

RH133-RH133-RHEL5-en-1-20070321





Default File Permissions

- Read and write (not execute) for all is the default for files
- Read, write and execute is the default for directories
- umask can be used to withhold permissions on file creation
- Users' umask is 022
 - Files will have permissions of 644
 - Directories will have permissions of 755
 - May need to change to 002 for group collaboration

RH133-RH133-RHEL5-en-1-20070321





Access Control Lists (ACLs)

- Grant rwx access to files and directories for multiple users or groups
 - o mount -o acl /directory
 - getfacl file | directory
 - o setfacl -m u:gandolf:rwx file | directory
 - o setfacl -m g:nazgul:rw file | directory
 - o setfacl -m d:u:frodo:rw directory
 - o setfacl -x u:samwise file | directory

RH133-RH133-RHEL5-en-1-20070321





SELinux

- Mandatory Access Control (MAC) -vs-Discretionary Access Control (DAC)
- A rule set called the *policy* determines how strict the control
- Processes are either restricted or unconfined
- The policy defines what resources restricted processes are allowed to access
- Any action that is not explicitly allowed is, by default, denied

RH133-RH133-RHEL5-en-1-20070321





SELinux, continued

- All files and processes have a security context
- The context has several elements, depending on the security needs
 - user:role:type:sensitivity:category
 - o user_u:object_r:tmp_t:s0:c0
 - Not all systems will display s0:c0
- Is -Z
- ps -Z
 - Usually paired with other options, such as -e

RH133-RH133-RHEL5-en-1-20070321





SELinux: Targeted Policy

- The targeted policy is loaded at install time
- Most local processes are unconfined
- Principally uses the type element for type enforcement
- The security context can be changed with chcon
 - chcon -t tmp_t /etc/hosts
- Safer to use restorecon
 - restorecon /etc/hosts

RH133-RH133-RHEL5-en-1-20070321





SELinux: Management

- Modes: Enforcing, Permissive, Disabled
 - Changing enforcement is allowed in the Targeted policy
 - getenforce
 - o setenforce 0 | 1
 - Disable from GRUB with selinux=0
- /etc/sysconfig/selinux
- system-config-securitylevel
 - o Change mode, Disabling requires reboot
- system-config-selinux
 - Booleans
- setroubleshootd
 - Advises on how to avoid errors, not ensure security!

RH133-RH133-RHEL5-en-1-20070321





End of Unit 5

- Questions and Answers
- Summary
 - User and Group accounts
 - File ownership and permissions
 - Extended file modes: SUID / SGID / Sticky
 - Switching accounts with su
 - umask and the UPG scheme
 - Shell environment
 - Setup NIS and LDAP
 - Use ACLs
 - Configure and troubleshoot SELinux

RH133-RH133-RHEL5-en-1-20070321





Filesystem Management

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Understand filesystem hierarchy
- Manage virtual memory
- Add new drives and partitions
- Mount NFS filesystems

RH133-RH133-RHEL5-en-1-20070321





Overview: Adding New Filesystems to the Filesystem Tree

- Identify Device
- Partition Device
- Make Filesystem
- Label Filesystem
- Create entry in /etc/fstab
- Mount New Filesystem

RH133-RH133-RHEL5-en-1-20070321





Device Recognition

- Master Boot Record (MBR) contains:
 - Executable code to load operating system
 - Space for partition table information, including:
 - Partition id or type
 - Starting cylinder for partition
 - Number of cylinders for partition

RH133-RH133-RHEL5-en-1-20070321





Disk Partitioning

- An extended partition points to additional partition descriptors
- Total maximum number of partitions supported by the kernel:
 - o 63 for IDE drives
 - o 15 for SCSI drives
- Why partition drives?
 - o containment, performance, quotas, recovery

RH133-RH133-RHEL5-en-1-20070321





Managing Partitions

- Create partitions using:
 - o fdisk
 - o sfdisk
 - GNU parted advanced partition manipulation (create, copy, resize, etc.)
- partprobe reinitializes the kernel's inmemory version of the partition table

RH133-RH133-RHEL5-en-1-20070321





Making Filesystems

- mkfs
- mkfs.ext2, mkfs.ext3, mkfs.msdos
- Specific filesystem utilities can be called directly
 - o mke2fs [options] device

RH133-RH133-RHEL5-en-1-20070321





Filesystem Labels

- Alternate way to refer to devices
- Device independent
 - o e2label special_dev_file [fslabel]
 - o mount [options] LABEL=fslabel
 mount_point
- **blkid** can be used to see labels and filesystem type of all devices.

RH133-RH133-RHEL5-en-1-20070321





tune2fs

- adjusts filesystem parameters
 - reserved blocks
 - o default mount options
 - o fsck frequency
- View current settings with dumpe2fs

RH133-RH133-RHEL5-en-1-20070321





Mount Points and /etc/fstab

- Configuration of the filesystem hierarchy
- Used by mount, fsck, and other programs
- Maintains the hierarchy between system reboots
- May use filesystem volume labels in the device field
- The mount -a command can be used to mount all filesystems listed in the /etc/fstab

RH133-RH133-RHEL5-en-1-20070321





Mounting Filesystems with mount

- mount [options] device mount_point
 - o -t vfstype (normally not needed)
 - o -o options
 - Default options: rw, suid, dev, exec, acl, and async

RH133-RH133-RHEL5-en-1-20070321





Unmounting Filesystems

- umount [options] device |
 mount_point
- You cannot unmount a filesystem that is in use
 - Use fuser to check and/or kill processes
- Use the **remount** option to change a mounted filesystem's options atomically
 - o mount -o remount, ro /data

RH133-RH133-RHEL5-en-1-20070321





mount By Example

- Sample filesystem requirements met using options:
 - Disabling execute access
 - Mounting a filesystem image
 - Mounting a PC-compatible filesystem
 - Disabling access time updates
 - Setting up a mount alias

RH133-RH133-RHEL5-en-1-20070321





Handling Swap Files and Partitions

- Swap space is a supplement to system RAM
- Basic setup involves:
 - Create swap partition or file
 - Write special signature using mkswap
 - o Add appropriate entries to /etc/fstab
 - Activate swap space with swapon -a

RH133-RH133-RHEL5-en-1-20070321





Mounting NFS Filesystems

- Makes a remote NFS filesystem work as though it were a local filesystem
- /etc/fstab can be used to specify persistent network mounts
- NFS shares are mounted at boot time by /etc/ init.d/netfs
- Exports can be mounted manually with the mount command.

```
# mkdir /mnt/server1
```

mount -t nfs server1:/var/ftp/pub /mnt/server1

RH133-RH133-RHEL5-en-1-20070321





Automounter

- System administrator specifies mount points controlled by automounter daemon process in / etc/auto.master
- The automounter monitors access to these directories and mounts the filesystem on demand
- Filesystems automatically unmounted after a specified interval of inactivity
- Enable the special map -host to "browse" all NFS exports on the network
- Supports wildcard directory names

RH133-RH133-RHEL5-en-1-20070321





Direct Maps

- Direct maps include absolute path names
- Does not obscure local directory structure
- Example:

```
/etc/auto.master:
/- /etc/auto.direct

/etc/auto.direct:
/foo server1:/export/foo
/usr/local/ server1:/usr/local
```

RH133-RH133-RHEL5-en-1-20070321





gnome-mount

- automatically mounts removable devices
- integrated with the HAL (Hardware Abstraction Layer)
- replaces fstab-sync

RH133-RH133-RHEL5-en-1-20070321





End of Unit 6

- Questions and Answers
- Summary
 - o What tools are available for partitioning?
 - o What two ways can swap space be implemented?
 - Mount NFS

RH133-RH133-RHEL5-en-1-20070321





Advanced Filesystem Management

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Setup filesystem quotas
- Setup and manage software Raid devices
- Configure Logical Volumes
- setup LVM Snapshots
- perform backups

RH133-RH133-RHEL5-en-1-20070321





Configuring the Quota System

- Overview
 - o Implemented within the kernel
 - Enabled on a per-filesystem basis
 - Individual policies for groups or users
 - Limit by the number of blocks or inodes
 - Implement both soft and hard limits
- Initialization
 - o Partition mount options: usrquota, grpquota
 - o Initialize database: quotacheck

RH133-RH133-RHEL5-en-1-20070321





Setting Quotas for Users

- Implementation
 - Start or stop quotas: quotaon, quotaoff
 - o Edit quotas directly: edquota username
 - o From a shell:

setquota username 4096 5120 40 50 /foo

o Define prototypical users:

edquota -p user1 user2

RH133-RH133-RHEL5-en-1-20070321





Reporting Quota Status

- Reporting
 - User inspection: quota
 - Quota overviews: repquota
 - o Miscellaneous utilities: warnquota

RH133-RH133-RHEL5-en-1-20070321





What is Software RAID?

- Multiple disks grouped together into "arrays" to provide better performance, redundancy or both.
- mdadm provides the administration interface to software RAID.
- Many "RAID Levels" supported, including RAID O, 1 and 5.
- Spare disks add extra redundancy
- RAID devices are named, /dev/md0, /dev/md1, /dev/md2, /dev/md3 and so on.

RH133-RH133-RHEL5-en-1-20070321





Software RAID Configuration

• Create and define RAID devices using mdadm

mdadm -C /dev/md0 -a yes -l 1 -n 2 -x 1 /dev/sda1 /dev/sdb1 /dev/sdc1

· Format each RAID device with a filesystem

mke2fs -j /dev/md0

- Test the RAID devices
- mdadm allows you to check the status of your RAID devices

mdadm --detail /dev/md0

Copyright © 2007 Red Hat, Inc. RH133-RH133-RHEL5-en-1-20070321 All rights reserved





Software RAID Testing and Recovery

Simulating disk failures

mdadm /dev/md0 -f /dev/sda1

- Recovering from a software RAID disk failure
 - o replace the failed hard drive and power on
 - o reconstruct partitions on the replacement drive
 - o mdadm /dev/md0 -a /dev/sda1
- mdadm, /proc/mdstat, and syslog messages


RH133-RH133-RHEL5-en-1-20070321





What is Logical Volume Manager (LVM)?

- A layer of abstraction that allows easy manipulation of volumes. Including resizing of filesystems
- Allows reorganization of filesystems across multiple physical devices
 - Devices are designated as Physical Volumes
 - o One or more Physical Volumes are used to create a Volume Group
 - Physical Volumes are defined with Physical Extents of a fixed size
 - Logical Volumes are created on Physical Volumes and are composed of Physical Extents
 - Filesystems may be created on Logical Volumes



RH133-RH133-RHEL5-en-1-20070321



Creating Logical Volumes

Create physical volumes

pvcreate /dev/hda3

- Assign physical volumes to volume groups
 vgcreate vg0 /dev/hda3
- Create logical volumes from volume groups

lvcreate -L 256M -n data vg0
mke2fs -j /dev/vg0/data

RH133-RH133-RHEL5-en-1-20070321





Resizing Logical Volumes

- Growing Volumes
 - o Ivextend can grow logical volumes
 - o resize2fs can grow EXT3 filesystems online
 - vgextend adds new physical volumes to an existing volume group.
- Shrinking volumes
 - Filesystem must be reduced first
 - Requires a filesystem check and cannot be performed online
 - o **Ivreduce** can then reduce the volume.
 - o Volume Groups can be reduced with:

pvmove /dev/hda3
vgreduce vg0 /dev/hda3

RH133-RH133-RHEL5-en-1-20070321





Logical Volume Manager Snapshots

- Snapshots are special Logical
 Volumes that are an exact copy of an existing Logical
 Volume at the time the snapshot is created
- Snapshots are perfect for backups and other operations where a temporary copy of an existing dataset is needed
- Snapshots only consume space where they are different from the original Logical Volume
 - Snapshots are allocated space at creation but do not use it until changes are made to the original Logical Volume or the Snapshot
 - When data is changed on the original Logical Volume the older data is copied to the Snapshot
 - Snapshots contain only data that has changed on the original Logical Volume or the Snapshot since the Snapshot was created.

RH133-RH133-RHEL5-en-1-20070321





Using LVM Snapshots

- Create Snapshot of existing Logical Volume
- # lvcreate -1 64 -s -n databackup /dev/vg0/data
- Mount Snapshot
- # mkdir -p /mnt/databackup
 # mount -o ro /dev/vg0/databackup /mnt/databackup
- Remove Snapshot
- # umount /mnt/databackup
- # lvremove /dev/vg0/databackup

RH133-RH133-RHEL5-en-1-20070321





Archiving tools: tar

- tar can backup to a file or tape device
- supports GZIP and BZIP2 compression
- can preserve file permissions, ownership and timestamps
- supports extended attributes
- uses rmt to write to a remote tape device

RH133-RH133-RHEL5-en-1-20070321





Archiving Tools: dump/restore

- Back up and restore ext2/3 filesystems
 - Does not work with other filesystems
 - dump should only be used on unmounted filesystems or filesystems that are read-only.
- Can do full or incremental backups
- Examples:

```
dump -0u -f /dev/nst0 /dev/hda2
restore -rf /dev/nst0
```

RH133-RH133-RHEL5-en-1-20070321





Archiving Tools: rsync:

- Efficiently copies files to or from remote systems
- Uses secure ssh connections for transport
 - o rsync *.conf barney:/home/joe/configs/
- Faster than scp copies differences in like files

RH133-RH133-RHEL5-en-1-20070321





End of Unit 7

- Questions and Answers
- Summary
 - Filesystem quotas
 - Configuration of Software RAID
 - Software RAID recovery
 - Configuration of Logical Volumes
 - LVM Snapshots
 - Backup Tools

RH133-RH133-RHEL5-en-1-20070321





Network Configuration

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- configure IP interfaces
- setup routes
- understand name resolution
- setup IPv6

RH133-RH133-RHEL5-en-1-20070321





Network Inferfaces

- Networking scripts refer to logical interface names:
 - o Ethernet: eth0, eth1 ...
 - o Dial-up: ppp0, ppp1 ...
 - o Loopback: lo
- Display network interfaces by using:
 - o ifconfig -a
 - o ip link [show]

RH133-RH133-RHEL5-en-1-20070321





Driver Selection

- All drivers for network interface cards are built as modules
- /etc/modprobe.conf maps logical names to specific modules:
 - o alias eth0 3c59x
- Secondary "card selection" can be specified in the interface configuration file, /etc/ sysconfig/network-scripts/ifcfgeth0
 - o HWADDR=00:0D:60:FB:CA:61

RH133-RH133-RHEL5-en-1-20070321





Speed and Duplex Settings

- Modules are configured to autonegotiate, by default
- Mismatches can cause intermittent to no communication
- Manually overridden using:
 - o ethtool
 - o ETHTOOL_OPTS in ifcfg-ethX
 - options or install in /etc/modprobe.conf
 for older interface modules

RH133-RH133-RHEL5-en-1-20070321





IPv4 Addresses

- View configuration with:
 - o ifconfig
 - o ip addr [show]

RH133-RH133-RHEL5-en-1-20070321





Dynamic IPv4 Configuration

- Interface configuration defined in:
 - o /etc/sysconfig/network-scripts/ifcfgethX
 - o Dynamic with line of: BOOTPROTO=dhcp
- Zero Configuration Networking
 - o Uses 169.254.0.0/16
 - Disabled with line of: NOZEROCONF=yes in /etc/ sysconfig/network-scripts/ifcfg-ethX
- Use **ifdown device**; **ifup device** to apply configuration changes

RH133-RH133-RHEL5-en-1-20070321





Static IPv4 Configuration

- Interface configuration defined in:
 - o /etc/sysconfig/network-scripts/ifcfgethX
- Static with lines of:
 - o BOOTPROTO=none
 - o IPADDR=10.0.0.1
 - o NETMASK=255.255.25.0

RH133-RH133-RHEL5-en-1-20070321





Device Aliases

- Useful for virtual hosting
- Bind multiple IP addresses to a single NIC
 - o eth1:1
 - o eth1:2
 - o eth1:3
- Create a separate interface configuration file for each device alias:
 - o ifcfg-ethX:xxx
 - Must use static networking

RH133-RH133-RHEL5-en-1-20070321





Routing Table

- Defines path to all systems
- View table with:
 - o route
 - o netstat -r
 - o ip route [show]

RH133-RH133-RHEL5-en-1-20070321





Default Gateway

- Used when no route entry is matched
- Might be obtained dynamically with DHCP
- Can be statically configured:
 - o With a line of: GATEWAY=10.53.0.254
 - o Globally in: /etc/sysconfig/network
 - OR, per interface in the interface configuration file: / etc/sysconfig/network-scripts/ifcfgethX

RH133-RH133-RHEL5-en-1-20070321





Configuring Routes

- To control traffic flow when there is more than one router
- Static routes defined per interface
 - o /etc/sysconfig/network-scripts/routeethX
 - Uses ip route add syntax
- Dynamic routes learned via daemon(s)
 - o quagga
 - o Support for various forms of RIP, OSPF, and BGP

RH133-RH133-RHEL5-en-1-20070321





Verify IP Connectivity

- ping
 - Network packet loss and latency measurement tool
- traceroute
 - Displays network path to a destination
- . mtr

RH133-RH133-RHEL5-en-1-20070321





Defining the Local Host Name

- View/Set local hostname with hostname
- Initially defined in /etc/sysconfig/

network:

- o HOSTNAME=stationX.example.com
- Might "pull" name from network
 - o dhclient daemon
 - "Reverse DNS Lookup"

RH133-RH133-RHEL5-en-1-20070321





Local Resolver

- Resolver performs forward and reverse lookups
- /etc/hosts
 - Local database of hostname to IP address mappings
 - Useful for small isolated networks
 - Normally, checked before DNS

RH133-RH133-RHEL5-en-1-20070321





Remote Resolvers

- /etc/resolv.conf
 - o Domains to search
 - Strict order of name servers to use
 - May be updated by dhclient
- /etc/nsswitch.conf
 - o Precendence of DNS versus /etc/hosts

RH133-RH133-RHEL5-en-1-20070321





Verify DNS Connectivity

- Verify name servers using:
 - o **nslookup** (deprecated)
 - o host
 - o dig

RH133-RH133-RHEL5-en-1-20070321





Network Configuration Utilities

- system-config-network
 - o system-config-network-gui
 - o system-config-network-tui
- Profile Selection
 - o system-config-network-cmd
 - o netprofile kernel argument

RH133-RH133-RHEL5-en-1-20070321





Transparent Dynamic Configuration

- NetworkManager service
- nm-applet

RH133-RH133-RHEL5-en-1-20070321





Implementing IPv6

- Kernel ipv6 module enables stateless autoconfiguration
- Additional configuration implemented by / etc/rc.d/init.d/network initialization script
 - o NETWORKING_IPV6=yes in /etc/sysconfig/ network
 - IPV6INIT=yes in /etc/sysconfig/networkscripts/ifcfg-ethX

RH133-RH133-RHEL5-en-1-20070321





IPv6: Dynamic Interface Configuration

- Two ways to dynamically configure IPv6 addresses:
 - Router Advertisement Daemon
 - Runs on (Linux) Default Gateway radvd
 - Only specifies prefix and default gateway
 - Enabled with IPV6_AUTOCONF=yes
 - Interface ID automatically generated based on the MAC address of the system
 - DHCP version 6
 - dhcp6s supports more configuration options
 - Enabled with DHCPV6C=yes

RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



8-21



IPv6: StaticInterface Configuration

- /etc/sysconfig/network-scripts/ ifcfg-ethX
 - o IPV6ADDR=<ipv6_address>[/prefix_length]
 - Device aliases unnecessary...
 - o IPV6ADDR_SECONDARIES=<ipv6_address>[/
 prefix_length] [...]

RH133-RH133-RHEL5-en-1-20070321





IPv6: Routing Configuration

- Default Gateway
 - Dynamically from radvd or dhcpv6s
 - o Manually specified in /etc/sysconfig/network
 - IPV6_DEFAULTGW=<IPv6_address[%
 interface]>
 - IPV6_DEFAULTDEV=<interface> only valid on point-to-point interfaces
- Static Routes
 - Defined per interface in /etc/sysconfig/ network-scripts/route6-ethX
 - Uses ip -6 route add syntax
 - <ipv6_network/prefix> via <ipv6_routeraddress>

RH133-RH133-RHEL5-en-1-20070321





New and Modified Utilities

- ping6
- traceroute6
- tracepath6
- ip -6
- host -t AAAA hostname6.domain6

RH133-RH133-RHEL5-en-1-20070321





End of Unit 8

- Questions and Answers
- Summary
 - o Where are drivers linked to specific interfaces?
 - o Where is a static IP address defined?
 - Where is the default route set?
 - o Where is the list of nameservers stored?

RH133-RH133-RHEL5-en-1-20070321





Unit 9

Installation

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Know important command line switches
- Understand different installation methods
- Create advanced partition layouts
- Understand Kickstart's role
- Create Kickstart files

RH133-RH133-RHEL5-en-1-20070321





Anaconda, the Red Hat Enterprise Linux Installer

- Supports different modes
 - Kickstart offers automated Installation
 - Upgrade performs an update of an existing Red Hat Enterprise Linux installation
 - Rescue Mode allows troubleshooting of unbootable systems
- Consists of two stages:
 - First stage starts the installation
 - Second stage performs the installation

RH133-RH133-RHEL5-en-1-20070321





First Stage: Starting the Installation

- The first stage consists of a installation kernel and an initrd.img
- Can be started with any supported boot loader
- Tasks of the First Stage:
 - Initializes the Installer
 - Parses command line arguments
 - Autodetects hardware
 - Loads additional drivers
 - Selects language, keyboard layout and installation method
 - Sets up networking if required for installation

RH133-RH133-RHEL5-en-1-20070321





First Stage: Boot Media

- Supported boot media:
 - o boot.iso or Installation CD/DVD
 - USB drive containing bootimg.img
 - Network boot with PXE
 - Other bootloaders such as GRUB
 - Boot floppies no longer supported
- Boot media can modified for custom installations

RH133-RH133-RHEL5-en-1-20070321





Accessing the Installer

- Graphical Installation
 - Default installation type
 - o Useful Switches: lowres, resolution, skipddc
- VNC based Installation
 - Activate with vnc and protect the session with vncpassword=password
 - Set network parameters with ip=IP Address and netmask=Network Mask
- Text based Installation
 - Started with the text switch
 - Menu-based terminal interface
- Serial Installation
 - Used automatically when no graphic card is detected
 - o Enable with: serial=device

RH133-RH133-RHEL5-en-1-20070321





First Stage: Installation Method

- Available Installation Methods:
 - Local CDROM
 - Hard drive
 - NFS image
 - o FTP
 - o HTTP
- Media sets:
 - o Two Sets available: Client and Server
 - Can be downloaded from Red Hat Network
 - May contain packages from additional layered products
 - An "Installation Key" must be entered to unlock additional content
 - Extra packages can also be installed after installation through RHN.

RH133-RH133-RHEL5-en-1-20070321





Network Installation Server

- Necessary for network-based installs
- Often faster than CDROM-based installation methods
- Provides an easy distribution platform for the enterprise
- Shares the RedHat directory via NFS, FTP and/or HTTP
- Can be used as a yum repository

RH133-RH133-RHEL5-en-1-20070321





Second Stage: Installation Overview

- Language and keyboard selection
- Installation Key
- Disk partitioning
- Bootloader configuration
- Network and time zone configuration
- Package selection

RH133-RH133-RHEL5-en-1-20070321





Configuring File Systems

- Must select mount points, partition sizes, and file system types in the installer
 - Can set up manually or automatically
- There are many layouts which may be used
 - o / must include /etc, /lib, /bin, /sbin
 - Swap space is typically 2x physical RAM
 - o Typical mount points: /boot, /home, /usr, /
 var, /tmp, /usr/local, /opt

RH133-RH133-RHEL5-en-1-20070321





Advanced Partitioning

Software RAID

- Create new partitions and select Software RAID as "filesystem" type
- Combine RAID partitions into a RAID device with RAID

LVM

- Select Physical Volume to create physical volumes
- LVM creates a Volume Group
- Add creates new Logical Volumes

RH133-RH133-RHEL5-en-1-20070321





Package Selection

- A default set of packages is automatically installed
- Select Customize now to change the default set of packages
- Customizing is necessary to add support for additional languages
- Anaconda automatically resolves package dependencies
- Package set can easily customized after install with yum or system-config-packages

RH133-RH133-RHEL5-en-1-20070321





First Boot: Post-Install Configuration

- Configure X Window System if necessary
- Firewall and SELinux Setup
- Kdump setup
- Set date and time
- Register with Red Hat Network and get updated RPMs
- Setup users
- Configure sound card
- Install additional RPMs or Red Hat documentation from CDROM

RH133-RH133-RHEL5-en-1-20070321





Kickstart

- Scripted Installation method
- Supports all Anaconda features
- /root/anaconda-ks.cfg is automatically created during Install
- Configuration utility: system-configkickstart
- Syntax-checker: ksvalidator

RH133-RH133-RHEL5-en-1-20070321





Starting a Kickstart Installation

- Anaconda enters Kickstart mode, when the ks boot option is specified
- ks queries DHCP for the Kickstart location
- ks=ur1 gets the file via HTTP, FTP, or NFS
- From a local medium: ks=floppy,
 ks=cdrom, or ks=hd:device:/path/to/
 file

RH133-RH133-RHEL5-en-1-20070321





Anatomy of a Kickstart File

- Commands section
 - Configures the system
 - o Ommited directives are prompted to the user
- %packages Section
 - Selects packages and groups for installation
 - o Dependcies are always resolved
- Scripts section(s)
 - Optional section to customize the system
 - o %pre scripts are run before installation
 - o %post scripts are run after installation

RH133-RH133-RHEL5-en-1-20070321





Kickstart: Commands Section Starting the Installation

- Installation Mode
 - o install performs a fresh install.
 - o upgrade upgrades an existing installation.
- Installation Method:

```
cdrom
url --url url
nfs --server host --path directory
harddrive --partition=device --dir=/path/to/install_tree
```

RH133-RH133-RHEL5-en-1-20070321





Kickstart: Commands section Important Directives

Required Directives

- Must be specified, otherwise the installer configures them interactively
- o Localization options: keyboard, lang, timezone
- o Authentication: rootpw, authconfig
- o Bootloader: bootloader

Optional Directives

- o Network: network [options]
- o Security: firewall, selinux, services
- Installer behaviour: firstboot, poweroff | reboot, interactive, text

RH133-RH133-RHEL5-en-1-20070321





Kickstart: Packages Section

- Add single packages with package_name without any version number
- Add package groups with @package_group
- Remove packages from the list: package_name
- Use wildcards to specify multiple packages
- Dependencies are always resolved
- Add support for additional languages with
 @lang-support
- Packages from layered products can be installed when an installation key is specified by with the key directive in the commands section.

RH133-RH133-RHEL5-en-1-20070321





Kickstart: %pre, %post

- %pre gives you the first word
 - o executes as a bash shell script
 - o executes after Kickstart file is parsed
- %post gives you the final word
 - Can specify interpreter (bash is default)
 - o chrooted by default, but may be run without chroot

RH133-RH133-RHEL5-en-1-20070321





End of Unit 9

- Questions and Answers
- Summary
 - Steps of the installation
 - Important Anaconda switches
 - system-config-kickstart
 - ksvalidator

RH133-RH133-RHEL5-en-1-20070321





Unit 10

Virtualization with Xen

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Define Virtualization
- Understand Xen Terminology
- Xen Tools

RH133-RH133-RHEL5-en-1-20070321





Virtualization with Xen

- Advantages of Virtualization
 - Effective resource usage
 - Managability
 - Security
- Key Concepts of Xen
 - Small Hypervisor
 - First "Domain" manages the system
 - o supports full and para virtualization

RH133-RH133-RHEL5-en-1-20070321





Hardware Considerations

- Minimum Requirements:
 - Processor with PAE support
 - o 256 MiB RAM per domain
 - o 6 GiB hard drive per domain
- Additional Considerations:
 - CPU with VT/SVM for Full Virtualization
 - Shared Storage for Live Migration
 - Actual Storage needs will vary by application

RH133-RH133-RHEL5-en-1-20070321





Preparing Domain-0

- Install the Domain0 as normal
- Boot the Xen hypervisor
- Start the xend management daemon

RH133-RH133-RHEL5-en-1-20070321





Virtual Resources

- CPU
 - uses VCPUs (Virtual CPUs)
 - need not map directly to real CPUs
- Storage
 - Block devices
 - Simple files
- Network Devices
 - Bridged or routed to Domain0
 - o By default mapped to xenbr0

RH133-RH133-RHEL5-en-1-20070321





Domain-U Configuration

- Defined Per Domain-U
- Virtual Block Devices
- CPUs
- Networking
- /etc/xen/domain

RH133-RH133-RHEL5-en-1-20070321





Installing a new Domain-U

- virt-manager
 - o Graphical frontend for managing domains
 - Provides a wizard for setting up new domains
 - Command line alternative: xm
- Define name of the domain
- Select storage type and number of CPUs
- Specify the location of the installer and optionally a kickstart file

RH133-RH133-RHEL5-en-1-20070321





Domain Management with xm

- Command line management tool
- Controlling domains
 - o xm <create | destroy>
 - o xm <pause | unpause >
 - o xm <save|restore> filename
 - o xm <shutdown|reboot>
- Monitoring
 - o xm list
 - xentop
 - xen console

RH133-RH133-RHEL5-en-1-20070321





Activating Domains on boot

- xendomains Sys-V init script
- Starts/stops Domain-Us
- must link domain config files to /etc/xen/ auto

edhat. 10-

RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



End of Unit 10

- Questions and Answers
- Summary
 - Xen Terminology
 - o xm commands
 - xendomains

redhat. 10-

RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



Unit 11

Troubleshooting

RH133-RH133-RHEL5-en-1-20070321





Objectives

Upon completion of this unit, you should be able to:

- Develop a strategy for troubleshooting
- Fix problems in different areas of the Linux system
- Boot the system into various runlevels
- Use the Rescue environment

RH133-RH133-RHEL5-en-1-20070321





Method of Fault Analysis

- Characterize the problem
- Reproduce the problem
- Find further information
- Eliminate possible causes
- Try the easy things first
- Backup config files before changing

RH133-RH133-RHEL5-en-1-20070321





Fault Analysis: Gathering Data

- Useful commands
 - history
 - o grep
 - o diff
 - o find -cmin -60
 - o strace command
 - o tail-f logfile
- Generate additional information
 - o *.debug in syslog
 - o --debug option in application

RH133-RH133-RHEL5-en-1-20070321





Things to Check: X

- Never debug X while in runlevel 5!
- Try system-config-display first
- . X -probeonly
- Is /home or /tmp full, or has the user reached a hard quota?
- Is xfs running?

RH133-RH133-RHEL5-en-1-20070321





Things to Check: Networking

- Hostname resolution
 - o dig www.redhat.com
- IP configuration
 - o ifconfig
- Default gateway
 - o route -n
- Module specification
- Device activation

RH133-RH133-RHEL5-en-1-20070321





Order of the Boot Process

- Bootloader configuration
- Kernel
- /sbin/init
 - Starting init
- /etc/rc.d/rc.sysinit
- /etc/rc.d/rc, /etc/rc.d/rc?.d/
 - Entering runlevel X
- /etc/rc.d/rc.local
- . X

RH133-RH133-RHEL5-en-1-20070321





Filesystem Corruption

- Common after crash or improper shutdown
- ext2 mounted for writing marked "dirty"
 - o If not mounted or mounted read-only, "clean"
 - o if not mounted and "dirty", may be corrupted
 - o repair requires exhaustive check
- ext3 usually marked "clean"
 - o journal indicates if recovery is needed
 - o only need to check files recorded in journal

RH133-RH133-RHEL5-en-1-20070321





Filesystem Recovery

- If / has journal, kernel examines it at boot
- /etc/rc.d/rc.sysinit runs fsck on filesystems marked in /etc/fstab
- fsck is a front end to other programs
- A failed fsck must be run manually

RH133-RH133-RHEL5-en-1-20070321





Recovery Run-levels

- · Pass run-level to init
 - o on boot from GRUB splash screen
 - o from shell prompt using: init or telinit
- Runlevel 1
 - o Process rc.sysinit and rc1.d scripts
- Runlevel s, S, or single
 - o Process only rc.sysinit
- emergency
 - o Run **sulogin** only



RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



Rescue Environment

- Required when root filesystem is unavailable
- Non-system specific
- Boot from CDROM (boot.iso or CD #1)
- Boot from diskboot.img on USB key

redhat. 11-

RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



Rescue Environment Utilities

- Disk Maintenance Utilities
- Networking Utilities
- Miscellaneous Utilities
- Logging: /tmp/syslog or /tmp/ anaconda.log

edhat. 11-

RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



Rescue Environment Details

- Filesystem reconstruction
 - o Anaconda will ask if filesystems should be mounted
 - o /mnt/sysimage/*
 - o /mnt/source
 - \$PATH includes hard drive's directories
- Filesystem nodes
 - System-specific device files provided
 - o **mknod** knows major/minor #'s



RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved



End of Unit 11

- Questions and Answers
- Summary
 - What are some things to check for
 - o X problems?
 - o Services problems?
 - o Networking problems?
 - o Boot problems?
 - o How might you repair an ext2 filesystem?
 - o What are some alternate boot methods?



RH133-RH133-RHEL5-en-1-20070321 Copyright © 2007 Red Hat, Inc. All rights reserved