

---

# Documentazione di Yocto Project dev 20261003 (Ita)

*Release dev*

**The Linux Foundation**

(Traduzione: **Baldassarre Cesarano**)

**03 ott 2026**



|          |                                                                            |           |
|----------|----------------------------------------------------------------------------|-----------|
| <b>1</b> | <b>Build Rapida di un'Immagine con lo Yocto Project</b>                    | <b>1</b>  |
| 1.1      | Benvenuti! . . . . .                                                       | 1         |
| 1.2      | Distribuzione Linux Compatibile . . . . .                                  | 1         |
| 1.3      | Pacchetti dell'Host di Build . . . . .                                     | 2         |
| 1.4      | Installazione e utilizzo di bitbake-setup . . . . .                        | 3         |
| 1.5      | Building dell'Immagine . . . . .                                           | 6         |
| 1.6      | Personalizzazione della Build per un Hardware Specifico . . . . .          | 7         |
| 1.7      | Creazione di un Proprio Layer Generico . . . . .                           | 9         |
| 1.8      | Cosa Fare Ora? . . . . .                                                   | 9         |
| <b>2</b> | <b>Cosa sarebbe stato utile sapere sullo Yocto Project</b>                 | <b>11</b> |
| <b>3</b> | <b>Transizione a un ambiente personalizzato per lo sviluppo di sistemi</b> | <b>17</b> |
| <b>4</b> | <b>Manuale Introduttivo e Concetti di Yocto Project</b>                    | <b>21</b> |
| 4.1      | Introduzione a Yocto Project . . . . .                                     | 22        |
| 4.1.1    | Cos'è Yocto Project? . . . . .                                             | 22        |
| 4.1.2    | Il Modello a Layer di Yocto Project . . . . .                              | 25        |
| 4.1.3    | Componenti e Tool . . . . .                                                | 26        |
| 4.1.4    | Metodi di Sviluppo . . . . .                                               | 29        |
| 4.1.5    | Distribuzione Embedded di Riferimento (Poky) . . . . .                     | 30        |
| 4.1.6    | Workflow del Sistema di Build OpenEmbedded . . . . .                       | 31        |
| 4.1.7    | Alcuni Termini di Base . . . . .                                           | 32        |
| 4.2      | L'Ambiente di Sviluppo di Yocto Project . . . . .                          | 33        |
| 4.2.1    | Filosofia Open Source . . . . .                                            | 33        |
| 4.2.2    | Host di Sviluppo . . . . .                                                 | 34        |
| 4.2.3    | I Repository del Codice Sorgente di Yocto Project . . . . .                | 35        |
| 4.2.4    | Flussi di Lavoro Git e Yocto Project . . . . .                             | 37        |
| 4.2.5    | Git . . . . .                                                              | 39        |
| 4.2.6    | Licenze . . . . .                                                          | 43        |
| 4.3      | Concetti di Yocto Project . . . . .                                        | 43        |

|          |                                                                                                    |            |
|----------|----------------------------------------------------------------------------------------------------|------------|
| 4.3.1    | Componenti di Yocto Project . . . . .                                                              | 44         |
| 4.3.2    | Layer . . . . .                                                                                    | 45         |
| 4.3.3    | Concetti del Sistema di Build OpenEmbedded . . . . .                                               | 46         |
| 4.3.4    | Generazione di Toolchain di Cross-Sviluppo . . . . .                                               | 72         |
| 4.3.5    | Cache di Shared State . . . . .                                                                    | 75         |
| 4.3.6    | Dipendenze di Runtime Aggiunte Automaticamente . . . . .                                           | 83         |
| 4.3.7    | Fakeroot e Pseudo . . . . .                                                                        | 84         |
| 4.3.8    | Mappa dei Task di BitBake . . . . .                                                                | 85         |
| <b>5</b> | <b>Guida per i Collaboratori di Yocto Project e di OpenEmbedded</b>                                | <b>91</b>  |
| 5.1      | Identificazione del Componente . . . . .                                                           | 91         |
| 5.2      | Segnalazione di un Difetto in Yocto Project e in OpenEmbedded . . . . .                            | 91         |
| 5.3      | Guida di Stile per le Ricette . . . . .                                                            | 92         |
| 5.3.1    | Convenzioni di Nomenclatura delle Ricette . . . . .                                                | 92         |
| 5.3.2    | Politica sulle Versioni . . . . .                                                                  | 93         |
| 5.3.3    | Modifiche al Numero di Versione . . . . .                                                          | 93         |
| 5.3.4    | Formattazione delle Ricette . . . . .                                                              | 94         |
| 5.3.5    | Metadati della ricetta . . . . .                                                                   | 94         |
| 5.3.6    | Stato della Patch Upstream . . . . .                                                               | 98         |
| 5.3.7    | Patch CVE . . . . .                                                                                | 100        |
| 5.3.8    | Formato della Patch . . . . .                                                                      | 100        |
| 5.4      | Apportare Modifiche a un Componente . . . . .                                                      | 101        |
| 5.4.1    | Contribuire tramite mailing list: Perché non utilizzare flussi di lavoro basati sul web? . . . . . | 101        |
| 5.4.2    | Preparazione delle Modifiche per l'Invio . . . . .                                                 | 101        |
| 5.4.3    | Creazione di Patch . . . . .                                                                       | 105        |
| 5.4.4    | Validazione delle Patch con Patchtest . . . . .                                                    | 106        |
| 5.4.5    | Invio delle Patch via Email . . . . .                                                              | 107        |
| 5.4.6    | Uso di Script per il Push di una Modifica Upstream e il Pull Request . . . . .                     | 110        |
| 5.4.7    | Invio di Modifiche ai Branch di Rilascio Stabili . . . . .                                         | 112        |
| 5.4.8    | Considerazioni sulla Revisione delle Patch . . . . .                                               | 113        |
| 5.4.9    | Monitoraggio dello Stato delle Patch . . . . .                                                     | 114        |
| 5.4.10   | Accettazione del Codice Generato dall'IA . . . . .                                                 | 115        |
| <b>6</b> | <b>Yocto Project Reference Manual</b>                                                              | <b>117</b> |
| 6.1      | Requisiti di Sistema . . . . .                                                                     | 117        |
| 6.1.1    | Spazio Libero Minimo su Disco . . . . .                                                            | 118        |
| 6.1.2    | RAM Minima di Sistema . . . . .                                                                    | 118        |
| 6.1.3    | Distribuzioni Linux Supportate . . . . .                                                           | 118        |
| 6.1.4    | Pacchetti Richiesti per l'Host di Build . . . . .                                                  | 120        |
| 6.1.5    | Versioni richieste di Git, tar, Python, make e gcc . . . . .                                       | 128        |
| 6.2      | Architetture e Funzionalità Supportate da Yocto Project . . . . .                                  | 131        |
| 6.2.1    | Supporto Primario . . . . .                                                                        | 132        |
| 6.2.2    | Supporto Secondario . . . . .                                                                      | 134        |
| 6.2.3    | Untested . . . . .                                                                                 | 135        |
| 6.3      | Terminologia di Yocto Project . . . . .                                                            | 136        |



|        |                                                                  |     |
|--------|------------------------------------------------------------------|-----|
| 6.4    | Rilasci di Yocto Project e Iter dei Rilasci Stabili              | 146 |
| 6.4.1  | Cadenza dei Rilasci Major e Minor                                | 146 |
| 6.4.2  | Ciclo di Sviluppo                                                | 146 |
| 6.4.3  | Nomi in Codice delle Release Major                               | 147 |
| 6.4.4  | Iter per il Rilascio Stabile                                     | 147 |
| 6.4.5  | Politiche di Accettazione delle Patch per le Release Stabili/LTS | 148 |
| 6.4.6  | Aggiornamenti a Release Stabili                                  | 148 |
| 6.4.7  | Versioni con Supporto a Lungo Termine                            | 150 |
| 6.4.8  | Test e Garanzia di Qualità                                       | 151 |
| 6.5    | Struttura della Directory Sorgente                               | 152 |
| 6.5.1  | Componenti Principali di Primo Livello                           | 153 |
| 6.5.2  | La Directory di Build --- build/                                 | 156 |
| 6.5.3  | Metadati di OpenEmbedded-Core (OE-Core) --- meta/                | 164 |
| 6.6    | Classi                                                           | 166 |
| 6.6.1  | allarch                                                          | 167 |
| 6.6.2  | archiver                                                         | 167 |
| 6.6.3  | autotools*                                                       | 167 |
| 6.6.4  | barebox                                                          | 168 |
| 6.6.5  | base                                                             | 169 |
| 6.6.6  | bash-completion                                                  | 169 |
| 6.6.7  | bin_package                                                      | 169 |
| 6.6.8  | binconfig                                                        | 169 |
| 6.6.9  | binconfig-disabled                                               | 170 |
| 6.6.10 | buildhistory                                                     | 170 |
| 6.6.11 | buildstats                                                       | 170 |
| 6.6.12 | buildstats-summary                                               | 170 |
| 6.6.13 | cargo                                                            | 170 |
| 6.6.14 | cargo_c                                                          | 171 |
| 6.6.15 | cargo_common                                                     | 171 |
| 6.6.16 | cargo-update-recipe-crates                                       | 171 |
| 6.6.17 | ccache                                                           | 171 |
| 6.6.18 | chrpath                                                          | 172 |
| 6.6.19 | cmake                                                            | 172 |
| 6.6.20 | cmake-qemu                                                       | 172 |
| 6.6.21 | cml1                                                             | 172 |
| 6.6.22 | compress_doc                                                     | 173 |
| 6.6.23 | copyleft_compliance                                              | 173 |
| 6.6.24 | copyleft_filter                                                  | 173 |
| 6.6.25 | core-image                                                       | 173 |
| 6.6.26 | cpan*                                                            | 173 |
| 6.6.27 | create-spdx                                                      | 173 |
| 6.6.28 | cross                                                            | 174 |
| 6.6.29 | cross-canadian                                                   | 174 |
| 6.6.30 | crosssdk                                                         | 174 |
| 6.6.31 | cython                                                           | 174 |

|        |                            |     |
|--------|----------------------------|-----|
| 6.6.32 | debian                     | 174 |
| 6.6.33 | deploy                     | 174 |
| 6.6.34 | devicetree                 | 174 |
| 6.6.35 | devshell                   | 175 |
| 6.6.36 | devupstream                | 175 |
| 6.6.37 | externalsrc                | 176 |
| 6.6.38 | extrausers                 | 176 |
| 6.6.39 | features_check             | 177 |
| 6.6.40 | fontcache                  | 178 |
| 6.6.41 | fs-uuid                    | 178 |
| 6.6.42 | gconf                      | 178 |
| 6.6.43 | gettext                    | 178 |
| 6.6.44 | github-releases            | 178 |
| 6.6.45 | gnomebase                  | 179 |
| 6.6.46 | go                         | 179 |
| 6.6.47 | go-mod                     | 179 |
| 6.6.48 | go-mod-update-modules      | 179 |
| 6.6.49 | go-vendor                  | 179 |
| 6.6.50 | gobject-introspection      | 179 |
| 6.6.51 | grub-efi                   | 180 |
| 6.6.52 | gsettings                  | 180 |
| 6.6.53 | gtk-doc                    | 180 |
| 6.6.54 | gtk-icon-cache             | 180 |
| 6.6.55 | gtk-immodules-cache        | 181 |
| 6.6.56 | gzipnative                 | 181 |
| 6.6.57 | image                      | 181 |
| 6.6.58 | image-buildinfo            | 181 |
| 6.6.59 | image_types                | 181 |
| 6.6.60 | image-container            | 182 |
| 6.6.61 | image-live                 | 183 |
| 6.6.62 | insane                     | 183 |
| 6.6.63 | kernel                     | 183 |
| 6.6.64 | kernel-arch                | 184 |
| 6.6.65 | kernel-devicetree          | 184 |
| 6.6.66 | kernel-fit-image           | 184 |
| 6.6.67 | kernel-fit-extra-artifacts | 186 |
| 6.6.68 | kernel-grub                | 187 |
| 6.6.69 | kernel-module-split        | 187 |
| 6.6.70 | kernel-uboot               | 187 |
| 6.6.71 | kernel-uimage              | 187 |
| 6.6.72 | kernel-yocto               | 187 |
| 6.6.73 | kernel-yocto-rust          | 187 |
| 6.6.74 | kernelsrc                  | 187 |
| 6.6.75 | lib_package                | 187 |
| 6.6.76 | libc*                      | 187 |

|         |                         |     |
|---------|-------------------------|-----|
| 6.6.77  | license                 | 187 |
| 6.6.78  | linuxloader             | 188 |
| 6.6.79  | logging                 | 188 |
| 6.6.80  | meson                   | 188 |
| 6.6.81  | metadata_scm            | 188 |
| 6.6.82  | mime                    | 188 |
| 6.6.83  | mime-xdg                | 188 |
| 6.6.84  | mirrors                 | 188 |
| 6.6.85  | module                  | 189 |
| 6.6.86  | module-base             | 189 |
| 6.6.87  | module-rust             | 189 |
| 6.6.88  | multilib*               | 189 |
| 6.6.89  | native                  | 189 |
| 6.6.90  | nativesdk               | 190 |
| 6.6.91  | nopackages              | 190 |
| 6.6.92  | nospdx                  | 190 |
| 6.6.93  | npm                     | 191 |
| 6.6.94  | overlayfs               | 191 |
| 6.6.95  | overlayfs-etc           | 192 |
| 6.6.96  | own-mirrors             | 193 |
| 6.6.97  | package                 | 193 |
| 6.6.98  | package_deb             | 194 |
| 6.6.99  | package_ipk             | 194 |
| 6.6.100 | package_rpm             | 194 |
| 6.6.101 | packagedata             | 194 |
| 6.6.102 | packagegroup            | 195 |
| 6.6.103 | patch                   | 195 |
| 6.6.104 | perlnative              | 195 |
| 6.6.105 | pypi                    | 195 |
| 6.6.106 | python_flit_core        | 195 |
| 6.6.107 | python_maturin          | 196 |
| 6.6.108 | python_mesonpy          | 196 |
| 6.6.109 | python_pbr              | 196 |
| 6.6.110 | python_pdm              | 196 |
| 6.6.111 | python_pep517           | 196 |
| 6.6.112 | python_poetry_core      | 196 |
| 6.6.113 | python_pyo3             | 196 |
| 6.6.114 | python_uv_build         | 197 |
| 6.6.115 | python-setuptools3_rust | 197 |
| 6.6.116 | pixbufcache             | 197 |
| 6.6.117 | pkgconfig               | 197 |
| 6.6.118 | populate_sdk            | 197 |
| 6.6.119 | populate_sdk_*          | 197 |
| 6.6.120 | prexport                | 198 |
| 6.6.121 | primport                | 198 |

|         |                              |     |
|---------|------------------------------|-----|
| 6.6.122 | prserv                       | 198 |
| 6.6.123 | pctest                       | 199 |
| 6.6.124 | pctest-cargo                 | 199 |
| 6.6.125 | pctest-gnome                 | 199 |
| 6.6.126 | pctest-python-pytest         | 199 |
| 6.6.127 | python3-dir                  | 199 |
| 6.6.128 | python3native                | 199 |
| 6.6.129 | python3targetconfig          | 199 |
| 6.6.130 | qemu                         | 200 |
| 6.6.131 | recipe_sanity                | 200 |
| 6.6.132 | relative_symlinks            | 200 |
| 6.6.133 | relocatable                  | 200 |
| 6.6.134 | remove-libtool               | 200 |
| 6.6.135 | report-error                 | 201 |
| 6.6.136 | retain                       | 201 |
| 6.6.137 | rm_work                      | 201 |
| 6.6.138 | rootfs*                      | 202 |
| 6.6.139 | rust                         | 202 |
| 6.6.140 | rust-common                  | 202 |
| 6.6.141 | rust-target-config           | 202 |
| 6.6.142 | sanity                       | 202 |
| 6.6.143 | sbom-cve-check               | 203 |
| 6.6.144 | sbom-cve-check-recipe        | 203 |
| 6.6.145 | scons                        | 203 |
| 6.6.146 | sdl                          | 203 |
| 6.6.147 | python_setuptools_build_meta | 203 |
| 6.6.148 | setuptools3                  | 204 |
| 6.6.149 | setuptools3_legacy           | 204 |
| 6.6.150 | setuptools3-base             | 204 |
| 6.6.151 | sign_rpm                     | 204 |
| 6.6.152 | siteinfo                     | 204 |
| 6.6.153 | sstate                       | 205 |
| 6.6.154 | staging                      | 205 |
| 6.6.155 | syslinux                     | 206 |
| 6.6.156 | systemd                      | 207 |
| 6.6.157 | systemd-boot                 | 207 |
| 6.6.158 | terminal                     | 207 |
| 6.6.159 | testexport                   | 208 |
| 6.6.160 | testimage                    | 208 |
| 6.6.161 | testsdk                      | 208 |
| 6.6.162 | texinfo                      | 209 |
| 6.6.163 | toaster                      | 209 |
| 6.6.164 | toolchain-scripts            | 209 |
| 6.6.165 | toolchain/clang              | 209 |
| 6.6.166 | toolchain/clang-native       | 209 |

|         |                                                         |     |
|---------|---------------------------------------------------------|-----|
| 6.6.167 | toolchain/gcc                                           | 210 |
| 6.6.168 | toolchain/gcc-native                                    | 210 |
| 6.6.169 | typecheck                                               | 210 |
| 6.6.170 | uboot-config                                            | 210 |
| 6.6.171 | uboot-extlinux-config                                   | 213 |
| 6.6.172 | uboot-sign                                              | 214 |
| 6.6.173 | uki                                                     | 215 |
| 6.6.174 | uninative                                               | 215 |
| 6.6.175 | update-alternatives                                     | 216 |
| 6.6.176 | update-rc.d                                             | 217 |
| 6.6.177 | upstream-stable-release-point                           | 217 |
| 6.6.178 | useradd*                                                | 217 |
| 6.6.179 | utility-tasks                                           | 218 |
| 6.6.180 | utils                                                   | 218 |
| 6.6.181 | vala                                                    | 218 |
| 6.6.182 | vex                                                     | 218 |
| 6.6.183 | waf                                                     | 218 |
| 6.6.184 | yocto-check-layer                                       | 219 |
| 6.7     | I Task                                                  | 219 |
| 6.7.1   | Normal Recipe Build Tasks                               | 219 |
| 6.7.2   | Manually Called Tasks                                   | 225 |
| 6.7.3   | Image-Related Tasks                                     | 227 |
| 6.7.4   | Kernel-Related Tasks                                    | 228 |
| 6.8     | Using Configuration Fragments                           | 230 |
| 6.8.1   | bitbake-config-build Quick Reference                    | 231 |
| 6.8.2   | Core Fragments                                          | 232 |
| 6.9     | devtool Quick Reference                                 | 234 |
| 6.9.1   | Getting Help                                            | 234 |
| 6.9.2   | The Workspace Layer Structure                           | 237 |
| 6.9.3   | Adding a New Recipe to the Workspace Layer              | 239 |
| 6.9.4   | Extracting the Source for an Existing Recipe            | 240 |
| 6.9.5   | Synchronizing a Recipe's Extracted Source Tree          | 240 |
| 6.9.6   | Modifying an Existing Recipe                            | 240 |
| 6.9.7   | Edit an Existing Recipe                                 | 241 |
| 6.9.8   | Updating a Recipe                                       | 241 |
| 6.9.9   | Checking on the Upgrade Status of a Recipe              | 241 |
| 6.9.10  | Upgrading a Recipe                                      | 243 |
| 6.9.11  | Resetting a Recipe                                      | 243 |
| 6.9.12  | Finish Working on a Recipe                              | 244 |
| 6.9.13  | Building Your Recipe                                    | 244 |
| 6.9.14  | Building dell'Imagine                                   | 244 |
| 6.9.15  | Deploying Your Software on the Target Machine           | 244 |
| 6.9.16  | Removing Your Software from the Target Machine          | 245 |
| 6.9.17  | Creating the Workspace Layer in an Alternative Location | 246 |
| 6.9.18  | Get the Status of the Recipes in Your Workspace         | 246 |

|          |                                                                        |            |
|----------|------------------------------------------------------------------------|------------|
| 6.9.19   | Search for Available Target Recipes . . . . .                          | 246        |
| 6.9.20   | Get Information on Recipe Configuration Scripts . . . . .              | 246        |
| 6.9.21   | Generate an IDE Configuration for a Recipe . . . . .                   | 247        |
| 6.10     | OpenEmbedded Kickstart (.wks) Reference . . . . .                      | 247        |
| 6.10.1   | Introduzione . . . . .                                                 | 247        |
| 6.10.2   | Command: part or partition . . . . .                                   | 247        |
| 6.10.3   | Command: bootloader . . . . .                                          | 250        |
| 6.10.4   | Directive: include . . . . .                                           | 250        |
| 6.11     | QA Error and Warning Messages . . . . .                                | 250        |
| 6.11.1   | Introduzione . . . . .                                                 | 250        |
| 6.11.2   | Errors and Warnings . . . . .                                          | 251        |
| 6.11.3   | Configuring and Disabling QA Checks . . . . .                          | 264        |
| 6.12     | Immagini . . . . .                                                     | 265        |
| 6.13     | Caratteristiche . . . . .                                              | 266        |
| 6.13.1   | Machine Features . . . . .                                             | 267        |
| 6.13.2   | Distro Features . . . . .                                              | 268        |
| 6.13.3   | Image Features . . . . .                                               | 270        |
| 6.13.4   | SDK Features . . . . .                                                 | 272        |
| 6.13.5   | Default Features . . . . .                                             | 272        |
| 6.14     | Glossario delle Variabili . . . . .                                    | 273        |
| 6.15     | Variable Context . . . . .                                             | 476        |
| 6.15.1   | Configuration . . . . .                                                | 476        |
| 6.15.2   | Ricette . . . . .                                                      | 477        |
| 6.16     | FAQ . . . . .                                                          | 478        |
| 6.16.1   | General questions . . . . .                                            | 480        |
| 6.16.2   | Building environment . . . . .                                         | 481        |
| 6.16.3   | Using the OpenEmbedded Build system . . . . .                          | 483        |
| 6.16.4   | Customizing generated images . . . . .                                 | 485        |
| 6.16.5   | Issues on the running system . . . . .                                 | 487        |
| 6.17     | Contributions and Additional Information . . . . .                     | 487        |
| 6.17.1   | Introduzione . . . . .                                                 | 487        |
| 6.17.2   | Contributions . . . . .                                                | 488        |
| 6.17.3   | Yocto Project Bugzilla . . . . .                                       | 488        |
| 6.17.4   | Mailing lists . . . . .                                                | 488        |
| 6.17.5   | Internet Relay Chat (IRC) . . . . .                                    | 489        |
| 6.17.6   | Links and Related Documentation . . . . .                              | 489        |
| <b>7</b> | <b>Manuale del Board Support Package (BSP) di Yocto Project</b>        | <b>491</b> |
| 7.1      | Manuale del Board Support Package (BSP) di Yocto Project . . . . .     | 491        |
| 7.1.1    | Layer BSP . . . . .                                                    | 491        |
| 7.1.2    | Preparazione dell'Host di Build per Lavorare con i Layer BSP . . . . . | 493        |
| 7.1.3    | Esempio di Struttura del Filesystem . . . . .                          | 495        |
| 7.1.4    | Sviluppo di un Board Support Package (BSP) . . . . .                   | 504        |
| 7.1.5    | Requisiti e Raccomandazioni per i BSP Rilasciati . . . . .             | 506        |
| 7.1.6    | Personalizzazione di una Ricetta per un BSP . . . . .                  | 509        |

|          |                                                                                                             |            |
|----------|-------------------------------------------------------------------------------------------------------------|------------|
| 7.1.7    | Considerazioni sulle Licenze BSP . . . . .                                                                  | 510        |
| 7.1.8    | Creazione di un Nuovo Layer BSP Tramite lo Script <code>bitbake-layers</code> . . . . .                     | 511        |
| <b>8</b> | <b>Manuale di Sviluppo dei Task di Yocto Project . . . . .</b>                                              | <b>517</b> |
| 8.1      | Il Manuale di Sviluppo dei Task di Yocto Project . . . . .                                                  | 517        |
| 8.1.1    | Benvenuti! . . . . .                                                                                        | 517        |
| 8.1.2    | Other Information . . . . .                                                                                 | 518        |
| 8.2      | Setting Up to Use the Yocto Project . . . . .                                                               | 518        |
| 8.2.1    | Creating a Team Development Environment . . . . .                                                           | 518        |
| 8.2.2    | Preparing the Build Host . . . . .                                                                          | 521        |
| 8.3      | Comprendere e Creare i Layer . . . . .                                                                      | 526        |
| 8.3.1    | Creating Your Own Layer . . . . .                                                                           | 526        |
| 8.3.2    | Following Best Practices When Creating Layers . . . . .                                                     | 528        |
| 8.3.3    | Making Sure Your Layer is Compatible With Yocto Project . . . . .                                           | 530        |
| 8.3.4    | Enabling Your Layer . . . . .                                                                               | 532        |
| 8.3.5    | Appending Other Layers Metadata With Your Layer . . . . .                                                   | 533        |
| 8.3.6    | Prioritizing Your Layer . . . . .                                                                           | 536        |
| 8.3.7    | Managing Layers . . . . .                                                                                   | 538        |
| 8.3.8    | Aggiungere un Layer Utilizzando lo Script <code>bitbake-layers</code> . . . . .                             | 540        |
| 8.3.9    | Saving and restoring the layers setup . . . . .                                                             | 541        |
| 8.4      | Customizing Images . . . . .                                                                                | 542        |
| 8.4.1    | Customizing Images Using <code>local.conf</code> . . . . .                                                  | 542        |
| 8.4.2    | Customizing Images Using Custom <code>IMAGE_FEATURES</code> and <code>EXTRA_IMAGE_FEATURES</code> . . . . . | 543        |
| 8.4.3    | Customizing Images Using Custom <code>.bb</code> Files . . . . .                                            | 544        |
| 8.4.4    | Customizing Images Using Custom Package Groups . . . . .                                                    | 544        |
| 8.4.5    | Customizing an Image Hostname . . . . .                                                                     | 545        |
| 8.5      | Scrivere una Nuova Ricetta . . . . .                                                                        | 546        |
| 8.5.1    | Overview . . . . .                                                                                          | 546        |
| 8.5.2    | Locate or Automatically Create a Base Recipe . . . . .                                                      | 547        |
| 8.5.3    | Storing and Naming the Recipe . . . . .                                                                     | 550        |
| 8.5.4    | Running a Build on the Recipe . . . . .                                                                     | 550        |
| 8.5.5    | Fetching Code . . . . .                                                                                     | 551        |
| 8.5.6    | Unpacking Code . . . . .                                                                                    | 553        |
| 8.5.7    | Patching Code . . . . .                                                                                     | 554        |
| 8.5.8    | Licenze . . . . .                                                                                           | 554        |
| 8.5.9    | Dependencies . . . . .                                                                                      | 554        |
| 8.5.10   | Configuring the Recipe . . . . .                                                                            | 555        |
| 8.5.11   | Using Headers to Interface with Devices . . . . .                                                           | 556        |
| 8.5.12   | Compilation . . . . .                                                                                       | 557        |
| 8.5.13   | Installing . . . . .                                                                                        | 558        |
| 8.5.14   | Enabling System Services . . . . .                                                                          | 559        |
| 8.5.15   | Packaging . . . . .                                                                                         | 559        |
| 8.5.16   | Sharing Files Between Recipes . . . . .                                                                     | 560        |
| 8.5.17   | Using Virtual Providers . . . . .                                                                           | 561        |
| 8.5.18   | Properly Versioning Pre-Release Recipes . . . . .                                                           | 562        |

|        |                                                                                |     |
|--------|--------------------------------------------------------------------------------|-----|
| 8.5.19 | Post-Installation Scripts . . . . .                                            | 563 |
| 8.5.20 | Testing . . . . .                                                              | 563 |
| 8.5.21 | Esempi . . . . .                                                               | 564 |
| 8.5.22 | Following Recipe Style Guidelines . . . . .                                    | 569 |
| 8.5.23 | Recipe Syntax . . . . .                                                        | 569 |
| 8.6    | Adding a New Machine . . . . .                                                 | 573 |
| 8.6.1  | Adding the Machine Configuration File . . . . .                                | 573 |
| 8.6.2  | Adding a Kernel for the Machine . . . . .                                      | 573 |
| 8.6.3  | Adding a Formfactor Configuration File . . . . .                               | 574 |
| 8.7    | Upgrading Recipes . . . . .                                                    | 574 |
| 8.7.1  | Using the Auto Upgrade Helper (AUH) . . . . .                                  | 575 |
| 8.7.2  | Using <code>devtool upgrade</code> . . . . .                                   | 577 |
| 8.7.3  | Manually Upgrading a Recipe . . . . .                                          | 580 |
| 8.8    | Finding Temporary Source Code . . . . .                                        | 581 |
| 8.9    | Creating New Configuration Fragments In Your Build . . . . .                   | 582 |
| 8.9.1  | Creating A Standard Configuration Fragment . . . . .                           | 583 |
| 8.9.2  | Creating A Built-in Fragment . . . . .                                         | 584 |
| 8.10   | Setting Up the Poky Reference Distro Manually . . . . .                        | 585 |
| 8.10.1 | Obtaining The Source Repositories . . . . .                                    | 585 |
| 8.10.2 | Building dell'Imagine . . . . .                                                | 586 |
| 8.11   | Using Quilt in Your Workflow . . . . .                                         | 587 |
| 8.12   | Using a Development Shell . . . . .                                            | 589 |
| 8.13   | Using a Python Development Shell . . . . .                                     | 590 |
| 8.14   | Building . . . . .                                                             | 591 |
| 8.14.1 | Building a Simple Image . . . . .                                              | 591 |
| 8.14.2 | Building Images for Multiple Targets Using Multiple Configurations . . . . .   | 592 |
| 8.14.3 | Building an Initial RAM Filesystem (Initramfs) Image . . . . .                 | 592 |
| 8.14.4 | Building a Tiny System . . . . .                                               | 595 |
| 8.14.5 | Building Images for More than One Machine . . . . .                            | 599 |
| 8.14.6 | Building Software from an External Source . . . . .                            | 601 |
| 8.14.7 | Replicating a Build Offline . . . . .                                          | 602 |
| 8.15   | Building Images for Multiple Targets With Multiconfig . . . . .                | 603 |
| 8.15.1 | Setting Up and Running a Multiple Configuration Build . . . . .                | 604 |
| 8.15.2 | Enabling Multiple Configuration Build Dependencies . . . . .                   | 606 |
| 8.15.3 | Suggested best practices . . . . .                                             | 607 |
| 8.15.4 | Common use case: building baremetal firmware alongside a Linux build . . . . . | 607 |
| 8.16   | Speeding Up a Build . . . . .                                                  | 609 |
| 8.17   | Limiting the Host Resources Usage . . . . .                                    | 610 |
| 8.18   | Working With Libraries . . . . .                                               | 613 |
| 8.18.1 | Including Static Library Files . . . . .                                       | 613 |
| 8.18.2 | Combining Multiple Versions of Library Files into One Image . . . . .          | 613 |
| 8.18.3 | Installing Multiple Versions of the Same Library . . . . .                     | 615 |
| 8.19   | Working with Pre-Built Libraries . . . . .                                     | 616 |
| 8.19.1 | Introduzione . . . . .                                                         | 616 |
| 8.19.2 | Versioned Libraries . . . . .                                                  | 616 |



|        |                                                                                                                               |     |
|--------|-------------------------------------------------------------------------------------------------------------------------------|-----|
| 8.19.3 | Non-Versioned Libraries . . . . .                                                                                             | 618 |
| 8.20   | Using the <code>devtool</code> command-line tool . . . . .                                                                    | 620 |
| 8.20.1 | Use <code>devtool add</code> to Add an Application . . . . .                                                                  | 620 |
| 8.20.2 | Use <code>devtool modify</code> to Modify the Source of an Existing Component . . . . .                                       | 624 |
| 8.20.3 | <code>devtool ide-sdk</code> configures IDEs and bootstraps SDKs . . . . .                                                    | 628 |
| 8.20.4 | Use <code>devtool upgrade</code> to Create a Version of the Recipe that Supports a Newer Version<br>of the Software . . . . . | 635 |
| 8.20.5 | A Closer Look at <code>devtool add</code> . . . . .                                                                           | 639 |
| 8.20.6 | Working With Recipes . . . . .                                                                                                | 642 |
| 8.20.7 | Restoring the Target Device to its Original State . . . . .                                                                   | 644 |
| 8.21   | Using x32 psABI . . . . .                                                                                                     | 645 |
| 8.22   | Enabling GObject Introspection Support . . . . .                                                                              | 646 |
| 8.22.1 | Enabling the Generation of Introspection Data . . . . .                                                                       | 646 |
| 8.22.2 | Disabling the Generation of Introspection Data . . . . .                                                                      | 647 |
| 8.22.3 | Testing that Introspection Works in an Image . . . . .                                                                        | 647 |
| 8.22.4 | Known Issues . . . . .                                                                                                        | 648 |
| 8.23   | Optionally Using an External Toolchain . . . . .                                                                              | 648 |
| 8.24   | Creating Partitioned Images Using Wic . . . . .                                                                               | 648 |
| 8.24.1 | Background . . . . .                                                                                                          | 649 |
| 8.24.2 | Requisiti . . . . .                                                                                                           | 649 |
| 8.24.3 | Getting Help . . . . .                                                                                                        | 650 |
| 8.24.4 | Operational Modes . . . . .                                                                                                   | 651 |
| 8.24.5 | Using an Existing Kickstart File . . . . .                                                                                    | 653 |
| 8.24.6 | Using the Wic Plugin Interface . . . . .                                                                                      | 655 |
| 8.24.7 | Wic Examples . . . . .                                                                                                        | 657 |
| 8.25   | Flashing Images Using <code>bmaptool</code> . . . . .                                                                         | 662 |
| 8.26   | Creating Your Own Distribution . . . . .                                                                                      | 663 |
| 8.26.1 | Copying and modifying the Poky distribution . . . . .                                                                         | 665 |
| 8.27   | Creating a Custom Template Configuration Directory . . . . .                                                                  | 665 |
| 8.28   | Conserving Disk Space . . . . .                                                                                               | 666 |
| 8.28.1 | Conserving Disk Space During Builds . . . . .                                                                                 | 666 |
| 8.28.2 | Purging Obsolete Shared State Cache Files . . . . .                                                                           | 667 |
| 8.29   | Working with Packages . . . . .                                                                                               | 667 |
| 8.29.1 | Excluding Packages from an Image . . . . .                                                                                    | 668 |
| 8.29.2 | Incrementing a Package Version . . . . .                                                                                      | 668 |
| 8.29.3 | Handling Optional Module Packaging . . . . .                                                                                  | 672 |
| 8.29.4 | Using Runtime Package Management . . . . .                                                                                    | 675 |
| 8.29.5 | Generating and Using Signed Packages . . . . .                                                                                | 679 |
| 8.29.6 | Testing Packages With <code>ptest</code> . . . . .                                                                            | 681 |
| 8.29.7 | Creating Node Package Manager (NPM) Packages . . . . .                                                                        | 681 |
| 8.29.8 | Adding custom metadata to packages . . . . .                                                                                  | 685 |
| 8.30   | Efficiently Fetching Source Files During a Build . . . . .                                                                    | 686 |
| 8.30.1 | Setting up Effective Mirrors . . . . .                                                                                        | 686 |
| 8.30.2 | Getting Source Files and Suppressing the Build . . . . .                                                                      | 686 |
| 8.31   | Selecting an Initialization Manager . . . . .                                                                                 | 687 |

|         |                                                                                      |     |
|---------|--------------------------------------------------------------------------------------|-----|
| 8.31.1  | Using SysVinit with udev . . . . .                                                   | 687 |
| 8.31.2  | Using BusyBox init with BusyBox mdev . . . . .                                       | 687 |
| 8.31.3  | Using systemd . . . . .                                                              | 688 |
| 8.32    | Selecting a Device Manager . . . . .                                                 | 689 |
| 8.32.1  | Using Persistent and Pre-Populated /dev . . . . .                                    | 689 |
| 8.32.2  | Using devtmpfs and a Device Manager . . . . .                                        | 689 |
| 8.33    | Using an External SCM . . . . .                                                      | 690 |
| 8.34    | Maintaining Build Output Quality with buildhistory . . . . .                         | 691 |
| 8.34.1  | Enabling and Disabling Build History . . . . .                                       | 692 |
| 8.34.2  | Understanding What the Build History Contains . . . . .                              | 692 |
| 8.35    | Debugging Tools and Techniques . . . . .                                             | 699 |
| 8.35.1  | Viewing Logs from Failed Tasks . . . . .                                             | 700 |
| 8.35.2  | Viewing Variable Values . . . . .                                                    | 700 |
| 8.35.3  | Viewing Package Information with oe-pkgdata-util . . . . .                           | 701 |
| 8.35.4  | Viewing Dependencies Between Recipes and Tasks . . . . .                             | 702 |
| 8.35.5  | Viewing Task Variable Dependencies . . . . .                                         | 703 |
| 8.35.6  | Debugging signature construction and unexpected task executions . . . . .            | 704 |
| 8.35.7  | Viewing Metadata Used to Create the Input Signature of a Shared State Task . . . . . | 705 |
| 8.35.8  | Invalidating Shared State to Force a Task to Run . . . . .                           | 705 |
| 8.35.9  | Running Specific Tasks . . . . .                                                     | 705 |
| 8.35.10 | General BitBake Problems . . . . .                                                   | 707 |
| 8.35.11 | Building with No Dependencies . . . . .                                              | 707 |
| 8.35.12 | Recipe Logging Mechanisms . . . . .                                                  | 708 |
| 8.35.13 | Debugging Parallel Make Races . . . . .                                              | 709 |
| 8.35.14 | Debugging With the GNU Project Debugger (GDB) Remotely . . . . .                     | 714 |
| 8.35.15 | Debugging with the GNU Project Debugger (GDB) on the Target . . . . .                | 718 |
| 8.35.16 | Enabling Minidebuginfo . . . . .                                                     | 719 |
| 8.35.17 | Other Debugging Tips . . . . .                                                       | 719 |
| 8.36    | Working With Licenses . . . . .                                                      | 720 |
| 8.36.1  | Tracking License Changes . . . . .                                                   | 721 |
| 8.36.2  | Enabling Commercially Licensed Recipes . . . . .                                     | 722 |
| 8.36.3  | Maintaining Open Source License Compliance During Your Product's Lifecycle . . . . . | 725 |
| 8.36.4  | Copying Non Standard Licenses . . . . .                                              | 729 |
| 8.37    | Creating a Software Bill of Materials . . . . .                                      | 729 |
| 8.38    | Using the Error Reporting Tool . . . . .                                             | 730 |
| 8.38.1  | Enabling and Using the Tool . . . . .                                                | 731 |
| 8.38.2  | Disabling the Tool . . . . .                                                         | 731 |
| 8.38.3  | Setting Up Your Own Error Reporting Server . . . . .                                 | 732 |
| 8.39    | Using Wayland and Weston . . . . .                                                   | 732 |
| 8.39.1  | Enabling Wayland in an Image . . . . .                                               | 732 |
| 8.39.2  | Running Weston . . . . .                                                             | 733 |
| 8.40    | Using the Quick EMUlator (QEMU) . . . . .                                            | 733 |
| 8.40.1  | Overview . . . . .                                                                   | 733 |
| 8.40.2  | Running QEMU . . . . .                                                               | 734 |
| 8.40.3  | Switching Between Consoles . . . . .                                                 | 736 |

|          |                                                                    |            |
|----------|--------------------------------------------------------------------|------------|
| 8.40.4   | Removing the Splash Screen . . . . .                               | 736        |
| 8.40.5   | Disabling the Cursor Grab . . . . .                                | 736        |
| 8.40.6   | Running Under a Network File System (NFS) Server . . . . .         | 736        |
| 8.40.7   | QEMU CPU Compatibility Under KVM . . . . .                         | 737        |
| 8.40.8   | QEMU Performance . . . . .                                         | 737        |
| 8.40.9   | QEMU Command-Line Syntax . . . . .                                 | 738        |
| 8.40.10  | runqemu Command-Line Options . . . . .                             | 739        |
| 8.41     | Locking and Unlocking Recipes Using bblock . . . . .               | 741        |
| 8.41.1   | Locking tasks and recipes . . . . .                                | 741        |
| 8.41.2   | Unlocking tasks and recipes . . . . .                              | 742        |
| 8.41.3   | Configuration file . . . . .                                       | 742        |
| 8.41.4   | Locking mechanism . . . . .                                        | 742        |
| 8.41.5   | Example . . . . .                                                  | 742        |
| 8.42     | Setting up a Shared State Cache Mirror . . . . .                   | 743        |
| 8.42.1   | Use-case . . . . .                                                 | 744        |
| 8.42.2   | Server Setup . . . . .                                             | 744        |
| 8.42.3   | Client Configuration . . . . .                                     | 745        |
| 8.42.4   | Going Further . . . . .                                            | 745        |
| 8.42.5   | Troubleshooting . . . . .                                          | 746        |
| 8.43     | Setting up a Hash Equivalence Server . . . . .                     | 747        |
| 8.43.1   | Hash Equivalence Server Setup . . . . .                            | 747        |
| 8.43.2   | Yocto Project Build Setup . . . . .                                | 748        |
| <b>9</b> | <b>Manuale di Sviluppo del Kernel Linux di Yocto Project</b>       | <b>751</b> |
| 9.1      | Introduzione . . . . .                                             | 751        |
| 9.1.1    | Overview . . . . .                                                 | 751        |
| 9.1.2    | Kernel Modification Workflow . . . . .                             | 752        |
| 9.2      | Common Tasks . . . . .                                             | 754        |
| 9.2.1    | Preparazione dell'Host di Build per Lavorare sul Kernel. . . . .   | 754        |
| 9.2.2    | Creating and Preparing a Layer . . . . .                           | 758        |
| 9.2.3    | Modifying an Existing Recipe . . . . .                             | 760        |
| 9.2.4    | Using devtool to Patch the Kernel . . . . .                        | 764        |
| 9.2.5    | Using Traditional Kernel Development to Patch the Kernel . . . . . | 767        |
| 9.2.6    | Configuring the Kernel . . . . .                                   | 770        |
| 9.2.7    | Expanding Variables . . . . .                                      | 777        |
| 9.2.8    | Working with a "Dirty" Kernel Version String . . . . .             | 777        |
| 9.2.9    | Working With Your Own Sources . . . . .                            | 778        |
| 9.2.10   | Working with Out-of-Tree Modules . . . . .                         | 779        |
| 9.2.11   | Inspecting Changes and Commits . . . . .                           | 781        |
| 9.2.12   | Adding Recipe-Space Kernel Features . . . . .                      | 782        |
| 9.3      | Working with Advanced Metadata (yocto-kernel-cache) . . . . .      | 783        |
| 9.3.1    | Overview . . . . .                                                 | 783        |
| 9.3.2    | Using Kernel Metadata in a Recipe . . . . .                        | 784        |
| 9.3.3    | Kernel Metadata Syntax . . . . .                                   | 785        |
| 9.3.4    | Kernel Metadata Location . . . . .                                 | 794        |

|           |                                                                                                      |            |
|-----------|------------------------------------------------------------------------------------------------------|------------|
| 9.3.5     | Organizing Your Source . . . . .                                                                     | 796        |
| 9.3.6     | SCC Description File Reference . . . . .                                                             | 798        |
| 9.4       | Advanced Kernel Concepts . . . . .                                                                   | 799        |
| 9.4.1     | Yocto Project Kernel Development and Maintenance . . . . .                                           | 799        |
| 9.4.2     | Yocto Linux Kernel Architecture and Branching Strategies . . . . .                                   | 800        |
| 9.4.3     | Kernel Build File Hierarchy . . . . .                                                                | 803        |
| 9.4.4     | Determining Hardware and Non-Hardware Features for the Kernel Configuration Audit<br>Phase . . . . . | 804        |
| 9.5       | Kernel Maintenance . . . . .                                                                         | 806        |
| 9.5.1     | Tree Construction . . . . .                                                                          | 806        |
| 9.5.2     | Build Strategy . . . . .                                                                             | 808        |
| 9.6       | Kernel Development FAQ . . . . .                                                                     | 809        |
| 9.6.1     | Common Questions and Solutions . . . . .                                                             | 809        |
| <b>10</b> | <b>Manuale di Sicurezza di Yocto Project</b>                                                         | <b>811</b> |
| 10.1      | Introduzione . . . . .                                                                               | 811        |
| 10.2      | Sicurezza del Processo di Build . . . . .                                                            | 812        |
| 10.3      | Come Rendere le Immagini più Sicure . . . . .                                                        | 812        |
| 10.3.1    | Considerazioni Generali . . . . .                                                                    | 813        |
| 10.3.2    | Flag di Sicurezza . . . . .                                                                          | 813        |
| 10.3.3    | Considerazioni Specifiche per il Sistema di Build OpenEmbedded . . . . .                             | 814        |
| 10.3.4    | Tool per Rafforzare la Sicurezza dell'Immagine . . . . .                                             | 815        |
| 10.4      | Verifica delle Vulnerabilità . . . . .                                                               | 815        |
| 10.4.1    | Vulnerabilità in OpenEmbedded-Core (OE-Core) . . . . .                                               | 815        |
| 10.4.2    | Verifica delle vulnerabilità in fase di build . . . . .                                              | 815        |
| 10.4.3    | Correzione delle mappature tra nome prodotto e versione CVE . . . . .                                | 818        |
| 10.4.4    | Correzione delle vulnerabilità nelle ricette . . . . .                                               | 818        |
| 10.4.5    | Dettagli di implementazione . . . . .                                                                | 821        |
| 10.4.6    | Vulnerabilità del kernel Linux . . . . .                                                             | 821        |
| 10.5      | Creazione di un Filesystem Root di Sola Lettura . . . . .                                            | 824        |
| 10.5.1    | Creazione del Filesystem Root . . . . .                                                              | 825        |
| 10.5.2    | Script di Post-Installazione e Filesystem Root di Sola Lettura . . . . .                             | 825        |
| 10.5.3    | Aree con Accesso in Scrittura . . . . .                                                              | 826        |
| 10.6      | Firma dello Stato Condiviso . . . . .                                                                | 826        |
| 10.6.1    | Requisiti dell'Host . . . . .                                                                        | 826        |
| 10.6.2    | Generazione di Una Coppia di Chiavi Pubblica e Privata con GPG . . . . .                             | 826        |
| 10.6.3    | Configurazione del Sistema di Build per la Firma degli Artefatti di Shared State . . . . .           | 827        |
| 10.6.4    | Verifica degli Artefatti Firmati dello Shared State . . . . .                                        | 829        |
| <b>11</b> | <b>Manuale di Profilazione e Tracing di Yocto Project</b>                                            | <b>833</b> |
| 11.1      | Manuale di Profilazione e Tracing di Yocto Project . . . . .                                         | 833        |
| 11.1.1    | Introduzione . . . . .                                                                               | 833        |
| 11.1.2    | Configurazione Generale . . . . .                                                                    | 833        |
| 11.2      | Architettura Generale dei Tool di Tracing e Profilazione di Linux . . . . .                          | 834        |
| 11.2.1    | Architettura dei Tool di Tracing e Profilazione . . . . .                                            | 834        |

|           |                                                                                                |            |
|-----------|------------------------------------------------------------------------------------------------|------------|
| 11.3      | Utilizzo di Base (con esempi) per ciascuno dei Tool di Tracing di Yocto . . . . .              | 835        |
| 11.3.1    | perf . . . . .                                                                                 | 835        |
| 11.3.2    | ftrace . . . . .                                                                               | 867        |
| 11.3.3    | SystemTap . . . . .                                                                            | 884        |
| 11.3.4    | Sysprof . . . . .                                                                              | 887        |
| 11.3.5    | LTtng (Linux Trace Toolkit, nuova generazione) . . . . .                                       | 889        |
| 11.3.6    | blktrace . . . . .                                                                             | 894        |
| 11.4      | Esempi Pratici . . . . .                                                                       | 902        |
| 11.4.1    | Velocità di Scrittura Ridotta sulle Immagini Live . . . . .                                    | 903        |
| <b>12</b> | <b>Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)</b> | <b>905</b> |
| 12.1      | Introduzione . . . . .                                                                         | 905        |
| 12.1.1    | SDK/eSDK Introduction . . . . .                                                                | 905        |
| 12.1.2    | SDK Development Model . . . . .                                                                | 907        |
| 12.2      | Using the Extensible SDK . . . . .                                                             | 909        |
| 12.2.1    | Why use the Extensible SDK and What is in It? . . . . .                                        | 909        |
| 12.2.2    | Installing the Extensible SDK . . . . .                                                        | 909        |
| 12.2.3    | Running the Extensible SDK Environment Setup Script . . . . .                                  | 912        |
| 12.2.4    | Using devtool in Your SDK Workflow . . . . .                                                   | 912        |
| 12.2.5    | Installing Additional Items Into the Extensible SDK . . . . .                                  | 913        |
| 12.2.6    | Applying Updates to an Installed Extensible SDK . . . . .                                      | 914        |
| 12.2.7    | Creating a Derivative SDK With Additional Components . . . . .                                 | 914        |
| 12.3      | Using the Standard SDK . . . . .                                                               | 915        |
| 12.3.1    | Why use the Standard SDK and What is in It? . . . . .                                          | 915        |
| 12.3.2    | Installing the SDK . . . . .                                                                   | 915        |
| 12.3.3    | Running the SDK Environment Setup Script . . . . .                                             | 917        |
| 12.4      | Using the SDK Toolchain Directly . . . . .                                                     | 917        |
| 12.4.1    | Autotools-Based Projects . . . . .                                                             | 917        |
| 12.4.2    | Makefile-Based Projects . . . . .                                                              | 921        |
| 12.5      | Obtaining the SDK . . . . .                                                                    | 926        |
| 12.5.1    | Working with the SDK components directly in a Yocto build . . . . .                            | 926        |
| 12.5.2    | Working with standalone SDK Installers . . . . .                                               | 926        |
| 12.5.3    | Extracting the Root Filesystem . . . . .                                                       | 928        |
| 12.5.4    | Installed Standard SDK Directory Structure . . . . .                                           | 929        |
| 12.5.5    | Installed Extensible SDK Directory Structure . . . . .                                         | 930        |
| 12.6      | Customizing the Extensible SDK standalone installer . . . . .                                  | 931        |
| 12.6.1    | Configuring the Extensible SDK . . . . .                                                       | 931        |
| 12.6.2    | Adjusting the Extensible SDK to Suit Your Build Host's Setup . . . . .                         | 932        |
| 12.6.3    | Changing the Extensible SDK Installer Title . . . . .                                          | 933        |
| 12.6.4    | Providing Updates to the Extensible SDK After Installation . . . . .                           | 933        |
| 12.6.5    | Changing the Default SDK Installation Directory . . . . .                                      | 934        |
| 12.6.6    | Providing Additional Installable Extensible SDK Content . . . . .                              | 934        |
| 12.6.7    | Minimizing the Size of the Extensible SDK Installer Download . . . . .                         | 935        |
| 12.7      | Customizing the Standard SDK . . . . .                                                         | 936        |
| 12.7.1    | Adding Individual Packages to the Standard SDK . . . . .                                       | 936        |

|           |                                                       |            |
|-----------|-------------------------------------------------------|------------|
| 12.7.2    | Adding API Documentation to the Standard SDK          | 936        |
| <b>13</b> | <b>Manuale Utente di Toaster</b>                      | <b>937</b> |
| 13.1      | Introduzione                                          | 937        |
| 13.1.1    | Funzionalità di Toaster                               | 937        |
| 13.1.2    | Opzioni di Installazione                              | 938        |
| 13.2      | Preparazione all'Uso di Toaster                       | 939        |
| 13.2.1    | Impostazione dei Requisiti di Sistema di Base         | 939        |
| 13.2.2    | Impostazione delle Dipendenze di Sistema di Toaster   | 939        |
| 13.3      | Configurazione e Utilizzo di Toaster                  | 940        |
| 13.3.1    | Avvio di Toaster per lo Sviluppo Locale               | 940        |
| 13.3.2    | Impostazione di Una Porta Diversa                     | 940        |
| 13.3.3    | Configurazione di Toaster Senza un Server Web         | 940        |
| 13.3.4    | Configurazione di Toaster Senza un Server di Build    | 941        |
| 13.3.5    | Configurazione dell'Accesso Esterno                   | 941        |
| 13.3.6    | La Directory per la Clonazione dei Layer              | 941        |
| 13.3.7    | La Build Directory                                    | 942        |
| 13.3.8    | Creazione di un Superutente Django                    | 942        |
| 13.3.9    | Configurazione di un'Istanza di Produzione di Toaster | 943        |
| 13.3.10   | Utilizzo dell'Interfaccia Web di Toaster              | 948        |
| 13.4      | Concetti e Riferimenti                                | 955        |
| 13.4.1    | Sorgenti dei Layer                                    | 955        |
| 13.4.2    | Release                                               | 957        |
| 13.4.3    | Configurazione di Toaster                             | 958        |
| 13.4.4    | Monitoraggio Remoto di Toaster                        | 961        |
| 13.4.5    | Comandi Utili                                         | 964        |
| <b>14</b> | <b>Manuale dell'Ambiente di Test di Yocto Project</b> | <b>967</b> |
| 14.1      | The Yocto Project Test Environment Manual             | 967        |
| 14.1.1    | Benvenuti!                                            | 967        |
| 14.1.2    | Yocto Project Autobuilder Overview                    | 968        |
| 14.1.3    | Yocto Project Tests --- Types of Testing Overview     | 969        |
| 14.1.4    | How Tests Map to Areas of Code                        | 970        |
| 14.1.5    | Test Examples                                         | 972        |
| 14.1.6    | Considerations When Writing Tests                     | 975        |
| 14.2      | Project Testing and Release Process                   | 976        |
| 14.2.1    | Day to Day Development                                | 976        |
| 14.2.2    | Release Builds                                        | 977        |
| 14.3      | Testing Packages With ptest                           | 977        |
| 14.3.1    | Adding ptest to Your Build                            | 978        |
| 14.3.2    | Running ptest                                         | 978        |
| 14.3.3    | Getting Your Package Ready                            | 979        |
| 14.4      | Performing Automated Runtime Testing                  | 980        |
| 14.4.1    | Enabling Tests                                        | 980        |
| 14.4.2    | Running Tests                                         | 985        |

|           |                                                                      |             |
|-----------|----------------------------------------------------------------------|-------------|
| 14.4.3    | Exporting Tests . . . . .                                            | 986         |
| 14.4.4    | Writing New Tests . . . . .                                          | 987         |
| 14.4.5    | Installing Packages in the DUT Without the Package Manager . . . . . | 989         |
| 14.5      | Understanding the Yocto Project Autobuilder . . . . .                | 990         |
| 14.5.1    | Execution Flow within the Autobuilder . . . . .                      | 990         |
| 14.5.2    | Autobuilder Target Execution Overview . . . . .                      | 991         |
| 14.5.3    | Autobuilder Technology . . . . .                                     | 992         |
| 14.5.4    | run-config Target Execution . . . . .                                | 993         |
| 14.5.5    | Deploying Yocto Autobuilder . . . . .                                | 994         |
| 14.6      | Reproducible Builds . . . . .                                        | 994         |
| 14.6.1    | How we define it . . . . .                                           | 994         |
| 14.6.2    | Why it matters . . . . .                                             | 994         |
| 14.6.3    | How we implement it . . . . .                                        | 995         |
| 14.6.4    | Can we prove the project is reproducible? . . . . .                  | 995         |
| 14.6.5    | How can I test my layer or recipes? . . . . .                        | 996         |
| 14.7      | Yocto Project Compatible . . . . .                                   | 997         |
| 14.7.1    | Introduzione . . . . .                                               | 997         |
| 14.7.2    | Benefits . . . . .                                                   | 997         |
| 14.7.3    | Validating a layer . . . . .                                         | 997         |
| <b>15</b> | <b>Manuale Utente di BitBake</b>                                     | <b>999</b>  |
| <b>16</b> | <b>Riferimento di Yocto Project Security</b>                         | <b>1001</b> |
| 16.1      | Team di sicurezza . . . . .                                          | 1001        |
| 16.1.1    | Nomina del team di sicurezza . . . . .                               | 1001        |
| 16.1.2    | Operazioni del Security Team . . . . .                               | 1001        |
| 16.1.3    | Membri del Team di Sicurezza . . . . .                               | 1003        |
| 16.2      | Segnalazione di Vulnerabilità . . . . .                              | 1003        |
| 16.2.1    | Come segnalare una potenziale vulnerabilità di sicurezza? . . . . .  | 1003        |
| <b>17</b> | <b>Informazioni sulla Release</b>                                    | <b>1005</b> |
| 17.1      | Introduzione . . . . .                                               | 1005        |
| 17.1.1    | General Migration Considerations . . . . .                           | 1005        |
| 17.2      | Release 6.1 (blacksail) . . . . .                                    | 1007        |
| 17.2.1    | Release notes for 6.1 (blacksail) . . . . .                          | 1007        |
| 17.2.2    | Migration notes for 6.1 (blacksail) . . . . .                        | 1038        |
| 17.3      | Release 6.0 (wrynose) . . . . .                                      | 1042        |
| 17.3.1    | Release notes for 6.0 (wrynose) . . . . .                            | 1042        |
| 17.3.2    | Migration notes for 6.0 (wrynose) . . . . .                          | 1074        |
| 17.3.3    | Release notes for Yocto-6.0.1 (Wrynose) . . . . .                    | 1082        |
| 17.3.4    | Release notes for Yocto-6.0.2 (Wrynose) . . . . .                    | 1089        |
| 17.3.5    | Release notes for Yocto-6.0.3 (Wrynose) . . . . .                    | 1096        |
| 17.4      | Release 5.3 (whinlatter) . . . . .                                   | 1105        |
| 17.4.1    | Release 5.3 (whinlatter) . . . . .                                   | 1105        |
| 17.4.2    | Release notes for 5.3 (whinlatter) . . . . .                         | 1111        |
| 17.4.3    | Release notes for Yocto-5.3.1 (Whinlatter) . . . . .                 | 1147        |

|         |                                            |      |
|---------|--------------------------------------------|------|
| 17.4.4  | Release notes for Yocto-5.3.2 (Whinlatter) | 1153 |
| 17.4.5  | Release notes for Yocto-5.3.3 (Whinlatter) | 1167 |
| 17.4.6  | Release notes for Yocto-5.3.4 (Whinlatter) | 1171 |
| 17.5    | Release 5.2 (walnascar)                    | 1177 |
| 17.5.1  | Release 5.2 (walnascar)                    | 1177 |
| 17.5.2  | Release notes for 5.2 (walnascar)          | 1182 |
| 17.5.3  | Release notes for Yocto-5.2.1 (Walnascar)  | 1214 |
| 17.5.4  | Release notes for Yocto-5.2.2 (Walnascar)  | 1218 |
| 17.5.5  | Release notes for Yocto-5.2.3 (Walnascar)  | 1224 |
| 17.5.6  | Release notes for Yocto-5.2.4 (Walnascar)  | 1232 |
| 17.6    | Release 5.1 (styhead)                      | 1239 |
| 17.6.1  | Release 5.1 (styhead)                      | 1239 |
| 17.6.2  | Release notes for 5.1 (styhead)            | 1242 |
| 17.6.3  | Release notes for Yocto-5.1.1 (Styhead)    | 1268 |
| 17.6.4  | Release notes for Yocto-5.1.2 (Styhead)    | 1278 |
| 17.6.5  | Release notes for Yocto-5.1.3 (Styhead)    | 1285 |
| 17.6.6  | Release notes for Yocto-5.1.4 (Styhead)    | 1289 |
| 17.7    | Release 5.0 (scarthgap)                    | 1292 |
| 17.7.1  | Release 5.0 LTS (scarthgap)                | 1292 |
| 17.7.2  | Release notes for 5.0 (scarthgap)          | 1295 |
| 17.7.3  | Release notes for Yocto-5.0.1 (Scarthgap)  | 1319 |
| 17.7.4  | Release notes for Yocto-5.0.2 (Scarthgap)  | 1322 |
| 17.7.5  | Release notes for Yocto-5.0.3 (Scarthgap)  | 1329 |
| 17.7.6  | Release notes for Yocto-5.0.4 (Scarthgap)  | 1340 |
| 17.7.7  | Release notes for Yocto-5.0.5 (Scarthgap)  | 1346 |
| 17.7.8  | Release notes for Yocto-5.0.6 (Scarthgap)  | 1352 |
| 17.7.9  | Release notes for Yocto-5.0.7 (Scarthgap)  | 1358 |
| 17.7.10 | Release notes for Yocto-5.0.8 (Scarthgap)  | 1365 |
| 17.7.11 | Release notes for Yocto-5.0.9 (Scarthgap)  | 1371 |
| 17.7.12 | Release notes for Yocto-5.0.10 (Scarthgap) | 1376 |
| 17.7.13 | Release notes for Yocto-5.0.11 (Scarthgap) | 1381 |
| 17.7.14 | Release notes for Yocto-5.0.12 (Scarthgap) | 1385 |
| 17.7.15 | Release notes for Yocto-5.0.13 (Scarthgap) | 1389 |
| 17.7.16 | Release notes for Yocto-5.0.14 (Scarthgap) | 1394 |
| 17.7.17 | Release notes for Yocto-5.0.15 (Scarthgap) | 1399 |
| 17.7.18 | Release notes for Yocto-5.0.16 (Scarthgap) | 1405 |
| 17.7.19 | Release notes for Yocto-5.0.17 (Scarthgap) | 1410 |
| 17.7.20 | Release notes for Yocto-5.0.18 (Scarthgap) | 1417 |
| 17.7.21 | Release notes for Yocto-5.0.19 (Scarthgap) | 1463 |
| 17.7.22 | Release notes for Yocto-5.0.20 (Scarthgap) | 1476 |
| 17.8    | Release 4.3 (nanbield)                     | 1492 |
| 17.8.1  | Release 4.3 (nanbield)                     | 1492 |
| 17.8.2  | Release notes for 4.3 (nanbield)           | 1496 |
| 17.8.3  | Release notes for Yocto-4.3.1 (Nanbield)   | 1519 |
| 17.8.4  | Release notes for Yocto-4.3.2 (Nanbield)   | 1526 |



|          |                                            |      |
|----------|--------------------------------------------|------|
| 17.8.5   | Release notes for Yocto-4.3.3 (Nanbield)   | 1533 |
| 17.8.6   | Release notes for Yocto-4.3.4 (Nanbield)   | 1538 |
| 17.9     | Release 4.2 (mickledore)                   | 1543 |
| 17.9.1   | Release 4.2 (mickledore)                   | 1543 |
| 17.9.2   | Release notes for 4.2 (mickledore)         | 1547 |
| 17.9.3   | Release notes for Yocto-4.2.1 (Mickledore) | 1574 |
| 17.9.4   | Release notes for Yocto-4.2.2 (Mickledore) | 1579 |
| 17.9.5   | Release notes for Yocto-4.2.3 (Mickledore) | 1589 |
| 17.9.6   | Release notes for Yocto-4.2.4 (Mickledore) | 1596 |
| 17.10    | Release 4.1 (langdale)                     | 1615 |
| 17.10.1  | Release 4.1 (langdale)                     | 1615 |
| 17.10.2  | Release notes for 4.1 (langdale)           | 1618 |
| 17.10.3  | Release notes for Yocto-4.1.1 (Langdale)   | 1640 |
| 17.10.4  | Release notes for Yocto-4.1.2 (Langdale)   | 1649 |
| 17.10.5  | Release notes for Yocto-4.1.3 (Langdale)   | 1657 |
| 17.10.6  | Release notes for Yocto-4.1.4 (Langdale)   | 1665 |
| 17.11    | Release 4.0 (kirkstone)                    | 1673 |
| 17.11.1  | Release 4.0 (kirkstone)                    | 1673 |
| 17.11.2  | Release notes for 4.0 (kirkstone)          | 1677 |
| 17.11.3  | Release notes for 4.0.1 (kirkstone)        | 1703 |
| 17.11.4  | Release notes for Yocto-4.0.2 (Kirkstone)  | 1710 |
| 17.11.5  | Release notes for Yocto-4.0.3 (Kirkstone)  | 1719 |
| 17.11.6  | Release notes for Yocto-4.0.4 (Kirkstone)  | 1728 |
| 17.11.7  | Release notes for Yocto-4.0.5 (Kirkstone)  | 1736 |
| 17.11.8  | Release notes for Yocto-4.0.6 (Kirkstone)  | 1741 |
| 17.11.9  | Release notes for Yocto-4.0.7 (Kirkstone)  | 1750 |
| 17.11.10 | Release notes for Yocto-4.0.8 (Kirkstone)  | 1756 |
| 17.11.11 | Release notes for Yocto-4.0.9 (Kirkstone)  | 1762 |
| 17.11.12 | Release notes for Yocto-4.0.10 (Kirkstone) | 1769 |
| 17.11.13 | Release notes for Yocto-4.0.11 (Kirkstone) | 1774 |
| 17.11.14 | Release notes for Yocto-4.0.12 (Kirkstone) | 1779 |
| 17.11.15 | Release notes for Yocto-4.0.13 (Kirkstone) | 1787 |
| 17.11.16 | Release notes for Yocto-4.0.14 (Kirkstone) | 1799 |
| 17.11.17 | Release notes for Yocto-4.0.15 (Kirkstone) | 1814 |
| 17.11.18 | Release notes for Yocto-4.0.16 (Kirkstone) | 1819 |
| 17.11.19 | Release notes for Yocto-4.0.17 (Kirkstone) | 1823 |
| 17.11.20 | Release notes for Yocto-4.0.18 (Kirkstone) | 1831 |
| 17.11.21 | Release notes for Yocto-4.0.19 (Kirkstone) | 1835 |
| 17.11.22 | Release notes for Yocto-4.0.20 (Kirkstone) | 1842 |
| 17.11.23 | Release notes for Yocto-4.0.21 (Kirkstone) | 1845 |
| 17.11.24 | Release notes for Yocto-4.0.22 (Kirkstone) | 1849 |
| 17.11.25 | Release notes for Yocto-4.0.23 (Kirkstone) | 1855 |
| 17.11.26 | Release notes for Yocto-4.0.24 (Kirkstone) | 1860 |
| 17.11.27 | Release notes for Yocto-4.0.25 (Kirkstone) | 1869 |
| 17.11.28 | Release notes for Yocto-4.0.26 (Kirkstone) | 1873 |

|          |                                                                                                                |      |
|----------|----------------------------------------------------------------------------------------------------------------|------|
| 17.11.29 | Release notes for Yocto-4.0.27 (Kirkstone)                                                                     | 1879 |
| 17.11.30 | Release notes for Yocto-4.0.28 (Kirkstone)                                                                     | 1883 |
| 17.11.31 | Release notes for Yocto-4.0.29 (Kirkstone)                                                                     | 1889 |
| 17.11.32 | Release notes for Yocto-4.0.30 (Kirkstone)                                                                     | 1893 |
| 17.11.33 | Release notes for Yocto-4.0.31 (Kirkstone)                                                                     | 1897 |
| 17.11.34 | Release notes for Yocto-4.0.32 (Kirkstone)                                                                     | 1902 |
| 17.11.35 | Release notes for Yocto-4.0.33 (Kirkstone)                                                                     | 1907 |
| 17.11.36 | Release notes for Yocto-4.0.34 (Kirkstone)                                                                     | 1912 |
| 17.11.37 | Release notes for Yocto-4.0.35 (Kirkstone)                                                                     | 1916 |
| 17.12    | Release 3.4 (honister)                                                                                         | 1921 |
| 17.12.1  | Migration notes for 3.4 (honister)                                                                             | 1921 |
| 17.12.2  | Release notes for 3.4 (honister)                                                                               | 1926 |
| 17.12.3  | Release notes for 3.4.1 (honister)                                                                             | 1949 |
| 17.12.4  | Release notes for 3.4.2 (honister)                                                                             | 1956 |
| 17.12.5  | Release notes for 3.4.3 (honister)                                                                             | 1963 |
| 17.12.6  | Release notes for 3.4.4 (honister)                                                                             | 1968 |
| 17.13    | Release 3.3 (hardknott)                                                                                        | 1972 |
| 17.13.1  | Minimum system requirements                                                                                    | 1972 |
| 17.13.2  | Removed recipes                                                                                                | 1972 |
| 17.13.3  | Single version common license file naming                                                                      | 1972 |
| 17.13.4  | New <code>python3targetconfig</code> class                                                                     | 1973 |
| 17.13.5  | <code>setup.py</code> path for Python modules                                                                  | 1973 |
| 17.13.6  | BitBake changes                                                                                                | 1973 |
| 17.13.7  | Packaging changes                                                                                              | 1974 |
| 17.13.8  | Miscellaneous changes                                                                                          | 1974 |
| 17.14    | Release 3.2 (gatesgarth)                                                                                       | 1974 |
| 17.14.1  | Minimum system requirements                                                                                    | 1975 |
| 17.14.2  | Removed recipes                                                                                                | 1975 |
| 17.14.3  | Removed classes                                                                                                | 1975 |
| 17.14.4  | pseudo path filtering and mismatch behaviour                                                                   | 1975 |
| 17.14.5  | <code>MLPREFIX</code> now required for multilib when runtime dependencies conditionally added                  | 1976 |
| 17.14.6  | <code>packagegroup-core-device-devel</code> no longer included in images built for <code>qemu*</code> machines | 1976 |
| 17.14.7  | DHCP server/client replaced                                                                                    | 1977 |
| 17.14.8  | Packaging changes                                                                                              | 1977 |
| 17.14.9  | Package QA check changes                                                                                       | 1977 |
| 17.14.10 | Globbering no longer supported in <code>file://</code> entries in <code>SRC_URI</code>                         | 1978 |
| 17.14.11 | <code>deploy</code> class now cleans <code>DEPLOYDIR</code> before <code>do_deploy</code>                      | 1978 |
| 17.14.12 | Custom SDK / SDK-style recipes need to include <code>nativesdk-sdk-provides-dummy</code>                       | 1978 |
| 17.14.13 | <code>ld.so.conf</code> now moved back to main <code>glibc</code> package                                      | 1978 |
| 17.14.14 | Host DRI drivers now used for GL support within <code>runqemu</code>                                           | 1979 |
| 17.14.15 | Initramfs images now use a blank suffix                                                                        | 1979 |
| 17.14.16 | Image artifact name variables now centralised in <code>image-artifact-names</code> class                       | 1979 |
| 17.14.17 | Miscellaneous changes                                                                                          | 1979 |
| 17.15    | Release 3.1 (dunfell)                                                                                          | 1980 |
| 17.15.1  | Minimum system requirements                                                                                    | 1980 |

|          |                                                                                                      |      |
|----------|------------------------------------------------------------------------------------------------------|------|
| 17.15.2  | mpc8315e-rdb machine removed . . . . .                                                               | 1980 |
| 17.15.3  | Python 2 removed . . . . .                                                                           | 1980 |
| 17.15.4  | Reproducible builds now enabled by default . . . . .                                                 | 1980 |
| 17.15.5  | Impact of ptest feature is now more significant . . . . .                                            | 1981 |
| 17.15.6  | Removed recipes . . . . .                                                                            | 1981 |
| 17.15.7  | features_check class replaces distro_features_check . . . . .                                        | 1981 |
| 17.15.8  | Removed classes . . . . .                                                                            | 1982 |
| 17.15.9  | SRC_URI checksum behaviour . . . . .                                                                 | 1982 |
| 17.15.10 | npm fetcher changes . . . . .                                                                        | 1982 |
| 17.15.11 | Packaging changes . . . . .                                                                          | 1983 |
| 17.15.12 | Additional warnings . . . . .                                                                        | 1983 |
| 17.15.13 | wic image type now used instead of live by default for x86 . . . . .                                 | 1983 |
| 17.15.14 | Miscellaneous changes . . . . .                                                                      | 1983 |
| 17.16    | Release 3.0 (zeus) . . . . .                                                                         | 1984 |
| 17.16.1  | Init System Selection . . . . .                                                                      | 1984 |
| 17.16.2  | LSB Support Removed . . . . .                                                                        | 1984 |
| 17.16.3  | Removed Recipes . . . . .                                                                            | 1984 |
| 17.16.4  | Packaging Changes . . . . .                                                                          | 1985 |
| 17.16.5  | CVE Checking . . . . .                                                                               | 1985 |
| 17.16.6  | BitBake Changes . . . . .                                                                            | 1986 |
| 17.16.7  | Sanity Checks . . . . .                                                                              | 1986 |
| 17.16.8  | Miscellaneous Changes . . . . .                                                                      | 1987 |
| 17.17    | Release 2.7 (warrior) . . . . .                                                                      | 1988 |
| 17.17.1  | BitBake Changes . . . . .                                                                            | 1988 |
| 17.17.2  | Eclipse Support Removed . . . . .                                                                    | 1988 |
| 17.17.3  | qemu-native Splits the System and User-Mode Parts . . . . .                                          | 1988 |
| 17.17.4  | The upstream-tracking.inc File Has Been Removed . . . . .                                            | 1988 |
| 17.17.5  | The DISTRO_FEATURES_LIBC Variable Has Been Removed . . . . .                                         | 1989 |
| 17.17.6  | License Value Corrections . . . . .                                                                  | 1989 |
| 17.17.7  | Packaging Changes . . . . .                                                                          | 1989 |
| 17.17.8  | Removed Recipes . . . . .                                                                            | 1989 |
| 17.17.9  | Removed Classes . . . . .                                                                            | 1990 |
| 17.17.10 | Miscellaneous Changes . . . . .                                                                      | 1990 |
| 17.18    | Release 2.6 (thud) . . . . .                                                                         | 1990 |
| 17.18.1  | GCC 8.2 is Now Used by Default . . . . .                                                             | 1990 |
| 17.18.2  | Removed Recipes . . . . .                                                                            | 1991 |
| 17.18.3  | Packaging Changes . . . . .                                                                          | 1992 |
| 17.18.4  | XOrg Protocol dependencies . . . . .                                                                 | 1992 |
| 17.18.5  | distutils and distutils3 Now Prevent Fetching Dependencies During the<br>do_configure Task . . . . . | 1993 |
| 17.18.6  | linux-yocto Configuration Audit Issues Now Correctly Reported . . . . .                              | 1993 |
| 17.18.7  | Image/Kernel Artifact Naming Changes . . . . .                                                       | 1993 |
| 17.18.8  | SERIAL_CONSOLE Deprecated . . . . .                                                                  | 1994 |
| 17.18.9  | Configure Script Reports Unknown Options as Errors . . . . .                                         | 1994 |
| 17.18.10 | Override Changes . . . . .                                                                           | 1994 |

|          |                                                                                |      |
|----------|--------------------------------------------------------------------------------|------|
| 17.18.11 | <code>systemd</code> Configuration is Now Split Into <code>systemd-conf</code> | 1995 |
| 17.18.12 | Automatic Testing Changes                                                      | 1995 |
| 17.18.13 | OpenSSL Changes                                                                | 1996 |
| 17.18.14 | BitBake Changes                                                                | 1996 |
| 17.18.15 | Security Changes                                                               | 1996 |
| 17.18.16 | Post Installation Changes                                                      | 1996 |
| 17.18.17 | Python 3 Profile-Guided Optimization                                           | 1996 |
| 17.18.18 | Miscellaneous Changes                                                          | 1997 |
| 17.19    | Release 2.5 (sumo)                                                             | 1997 |
| 17.19.1  | Packaging Changes                                                              | 1997 |
| 17.19.2  | Removed Recipes                                                                | 1998 |
| 17.19.3  | Scripts and Tools Changes                                                      | 1998 |
| 17.19.4  | BitBake Changes                                                                | 1999 |
| 17.19.5  | Python and Python 3 Changes                                                    | 1999 |
| 17.19.6  | Miscellaneous Changes                                                          | 2000 |
| 17.20    | Release 2.4 (rocko)                                                            | 2002 |
| 17.20.1  | Memory Resident Mode                                                           | 2002 |
| 17.20.2  | Packaging Changes                                                              | 2002 |
| 17.20.3  | Removed Recipes                                                                | 2003 |
| 17.20.4  | Kernel Device Tree Move                                                        | 2004 |
| 17.20.5  | Package QA Changes                                                             | 2004 |
| 17.20.6  | README File Changes                                                            | 2004 |
| 17.20.7  | Miscellaneous Changes                                                          | 2005 |
| 17.21    | Release 2.3 (pyro)                                                             | 2006 |
| 17.21.1  | Recipe-specific Sysroots                                                       | 2006 |
| 17.21.2  | <code>PATH</code> Variable                                                     | 2007 |
| 17.21.3  | Changes to Scripts                                                             | 2007 |
| 17.21.4  | Changes to Functions                                                           | 2008 |
| 17.21.5  | BitBake Changes                                                                | 2008 |
| 17.21.6  | Absolute Symbolic Links                                                        | 2009 |
| 17.21.7  | GPLv2 Versions of GPLv3 Recipes Moved                                          | 2009 |
| 17.21.8  | Package Management Changes                                                     | 2009 |
| 17.21.9  | Removed Recipes                                                                | 2010 |
| 17.21.10 | Wic Changes                                                                    | 2011 |
| 17.21.11 | QA Changes                                                                     | 2011 |
| 17.21.12 | Miscellaneous Changes                                                          | 2011 |
| 17.22    | Release 2.2 (morty)                                                            | 2013 |
| 17.22.1  | Minimum Kernel Version                                                         | 2013 |
| 17.22.2  | Staging Directories in Sysroot Has Been Simplified                             | 2013 |
| 17.22.3  | Removal of Old Images and Other Files in <code>tmp/deploy</code> Now Enabled   | 2013 |
| 17.22.4  | Python Changes                                                                 | 2013 |
| 17.22.5  | uClibc Replaced by musl                                                        | 2014 |
| 17.22.6  | <code>#{B}</code> No Longer Default Working Directory for Tasks                | 2014 |
| 17.22.7  | <code>runqemu</code> Ported to Python                                          | 2014 |
| 17.22.8  | Default Linker Hash Style Changed                                              | 2017 |

|          |                                                                |      |
|----------|----------------------------------------------------------------|------|
| 17.22.9  | KERNEL_IMAGE_BASE_NAME no Longer Uses KERNEL_IMAGETYPE         | 2017 |
| 17.22.10 | IMGDEPLOYDIR Replaces DEPLOY_DIR_IMAGE for Most Use Cases      | 2017 |
| 17.22.11 | BitBake Changes                                                | 2017 |
| 17.22.12 | Swabber has Been Removed                                       | 2018 |
| 17.22.13 | Removed Recipes                                                | 2018 |
| 17.22.14 | Removed Classes                                                | 2019 |
| 17.22.15 | Minor Packaging Changes                                        | 2019 |
| 17.22.16 | Miscellaneous Changes                                          | 2019 |
| 17.23    | Release 2.1 (krogoth)                                          | 2020 |
| 17.23.1  | Variable Expansion in Python Functions                         | 2020 |
| 17.23.2  | Overrides Must Now be Lower-Case                               | 2020 |
| 17.23.3  | Expand Parameter to getVar() and getVarFlag() is Now Mandatory | 2020 |
| 17.23.4  | Makefile Environment Changes                                   | 2020 |
| 17.23.5  | libexecdir Reverted to \${prefix}/libexec                      | 2021 |
| 17.23.6  | ac_cv_sizeof_off_t is No Longer Cached in Site Files           | 2021 |
| 17.23.7  | Image Generation is Now Split Out from Filesystem Generation   | 2021 |
| 17.23.8  | Removed Recipes                                                | 2021 |
| 17.23.9  | Class Changes                                                  | 2022 |
| 17.23.10 | Build System User Interface Changes                            | 2022 |
| 17.23.11 | ADT Removed                                                    | 2022 |
| 17.23.12 | Poky Reference Distribution Changes                            | 2023 |
| 17.23.13 | Packaging Changes                                              | 2024 |
| 17.23.14 | Tuning File Changes                                            | 2024 |
| 17.23.15 | Supporting GObject Introspection                               | 2024 |
| 17.23.16 | Miscellaneous Changes                                          | 2024 |
| 17.24    | Release 2.0 (jethro)                                           | 2025 |
| 17.24.1  | GCC 5                                                          | 2026 |
| 17.24.2  | Gstreamer 0.10 Removed                                         | 2026 |
| 17.24.3  | Removed Recipes                                                | 2026 |
| 17.24.4  | BitBake datastore improvements                                 | 2027 |
| 17.24.5  | Shell Message Function Changes                                 | 2027 |
| 17.24.6  | Extra Development/Debug Package Cleanup                        | 2027 |
| 17.24.7  | Recipe Maintenance Tracking Data Moved to OE-Core              | 2028 |
| 17.24.8  | Automatic Stale Sysroot File Cleanup                           | 2028 |
| 17.24.9  | linux-yocto Kernel Metadata Repository Now Split from Source   | 2028 |
| 17.24.10 | Additional QA checks                                           | 2029 |
| 17.24.11 | Miscellaneous Changes                                          | 2029 |
| 17.25    | Release 1.8 (fido)                                             | 2029 |
| 17.25.1  | Removed Recipes                                                | 2029 |
| 17.25.2  | BlueZ 4.x / 5.x Selection                                      | 2030 |
| 17.25.3  | Kernel Build Changes                                           | 2030 |
| 17.25.4  | SSL 3.0 is Now Disabled in OpenSSL                             | 2030 |
| 17.25.5  | Default Sysroot Poisoning                                      | 2031 |
| 17.25.6  | Rebuild Improvements                                           | 2031 |
| 17.25.7  | QA Check and Validation Changes                                | 2031 |

|          |                                                             |      |
|----------|-------------------------------------------------------------|------|
| 17.25.8  | Miscellaneous Changes                                       | 2031 |
| 17.26    | Release 1.7 (dizzy)                                         | 2032 |
| 17.26.1  | Changes to Setting QEMU PACKAGECONFIG Options in local.conf | 2032 |
| 17.26.2  | Minimum Git version                                         | 2032 |
| 17.26.3  | Autotools Class Changes                                     | 2032 |
| 17.26.4  | Binary Configuration Scripts Disabled                       | 2033 |
| 17.26.5  | eglibc 2.19 Replaced with glibc 2.20                        | 2033 |
| 17.26.6  | Kernel Module Autoloading                                   | 2033 |
| 17.26.7  | QA Check Changes                                            | 2034 |
| 17.26.8  | Removed Recipes                                             | 2034 |
| 17.26.9  | Miscellaneous Changes                                       | 2034 |
| 17.27    | Release 1.6 (daisy)                                         | 2035 |
| 17.27.1  | archiver Class                                              | 2035 |
| 17.27.2  | Packaging Changes                                           | 2035 |
| 17.27.3  | BitBake                                                     | 2035 |
| 17.27.4  | Changes to Variables                                        | 2036 |
| 17.27.5  | Package Test (ptest)                                        | 2037 |
| 17.27.6  | Build Changes                                               | 2038 |
| 17.27.7  | qemu-native                                                 | 2038 |
| 17.27.8  | core-image-basic                                            | 2038 |
| 17.27.9  | Licenze                                                     | 2038 |
| 17.27.10 | CFLAGS Options                                              | 2038 |
| 17.27.11 | Custom Image Output Types                                   | 2039 |
| 17.27.12 | I Task                                                      | 2039 |
| 17.27.13 | update-alternative Provider                                 | 2039 |
| 17.27.14 | virtclass Overrides                                         | 2039 |
| 17.27.15 | Removed and Renamed Recipes                                 | 2039 |
| 17.27.16 | Removed Classes                                             | 2040 |
| 17.27.17 | Reference Board Support Packages (BSPs)                     | 2040 |
| 17.28    | Release 1.5 (dora)                                          | 2040 |
| 17.28.1  | Host Dependency Changes                                     | 2040 |
| 17.28.2  | atom-pc Board Support Package (BSP)                         | 2040 |
| 17.28.3  | BitBake                                                     | 2041 |
| 17.28.4  | QA Warnings                                                 | 2041 |
| 17.28.5  | Directory Layout Changes                                    | 2041 |
| 17.28.6  | Shortened Git SRCREV Values                                 | 2042 |
| 17.28.7  | IMAGE_FEATURES                                              | 2042 |
| 17.28.8  | /run                                                        | 2042 |
| 17.28.9  | Removal of Package Manager Database Within Image Recipes    | 2042 |
| 17.28.10 | Images Now Rebuild Only on Changes Instead of Every Time    | 2043 |
| 17.28.11 | Task Recipes                                                | 2043 |
| 17.28.12 | BusyBox                                                     | 2043 |
| 17.28.13 | Automated Image Testing                                     | 2043 |
| 17.28.14 | Build History                                               | 2043 |
| 17.28.15 | udev                                                        | 2043 |

|           |                                         |             |
|-----------|-----------------------------------------|-------------|
| 17.28.16  | Removed and Renamed Recipes             | 2044        |
| 17.28.17  | Other Changes                           | 2044        |
| 17.29     | Release 1.4 (dylan)                     | 2044        |
| 17.29.1   | BitBake                                 | 2045        |
| 17.29.2   | Build Behavior                          | 2045        |
| 17.29.3   | Proxies and Fetching Source             | 2045        |
| 17.29.4   | Custom Interfaces File (netbase change) | 2045        |
| 17.29.5   | Remote Debugging                        | 2046        |
| 17.29.6   | Variables                               | 2046        |
| 17.29.7   | Target Package Management with RPM      | 2046        |
| 17.29.8   | Recipes Moved                           | 2046        |
| 17.29.9   | Removals and Renames                    | 2047        |
| 17.30     | Release 1.3 (danny)                     | 2047        |
| 17.30.1   | Local Configuration                     | 2048        |
| 17.30.2   | Ricette                                 | 2048        |
| 17.30.3   | Linux Kernel Naming                     | 2050        |
| <b>18</b> | <b>Supported Release Manuals</b>        | <b>2051</b> |
| 18.1      | Release Series 6.0 (wrynose)            | 2051        |
| 18.2      | Release Series 5.0 (scarthgap)          | 2051        |
| <b>19</b> | <b>Outdated Release Manuals</b>         | <b>2053</b> |
| 19.1      | Release Series 5.3 (whinlatter)         | 2053        |
| 19.2      | Release Series 5.2 (walnascar)          | 2053        |
| 19.3      | Release Series 5.1 (styhead)            | 2053        |
| 19.4      | Release Series 4.3 (nanbield)           | 2054        |
| 19.5      | Release Series 4.2 (mickledore)         | 2054        |
| 19.6      | Release Series 4.1 (langdale)           | 2054        |
| 19.7      | Release Series 4.0 (kirkstone)          | 2054        |
| 19.8      | Release Series 3.4 (honister)           | 2055        |
| 19.9      | Release Series 3.3 (hardknott)          | 2056        |
| 19.10     | Release Series 3.2 (gatesgarth)         | 2056        |
| 19.11     | Release Series 3.1 (dunfell)            | 2056        |
| 19.12     | Release Series 3.0 (zeus)               | 2057        |
| 19.13     | Release Series 2.7 (warrior)            | 2058        |
| 19.14     | Release Series 2.6 (thud)               | 2058        |
| 19.15     | Release Series 2.5 (sumo)               | 2058        |
| 19.16     | Release Series 2.4 (rocko)              | 2058        |
| 19.17     | Release Series 2.3 (pyro)               | 2058        |
| 19.18     | Release Series 2.2 (morty)              | 2059        |
| 19.19     | Release Series 2.1 (krogoth)            | 2059        |
| 19.20     | Release Series 2.0 (jethro)             | 2059        |
| 19.21     | Release Series 1.8 (fido)               | 2059        |
| 19.22     | Release Series 1.7 (dizzy)              | 2059        |
| 19.23     | Release Series 1.6 (daisy)              | 2060        |

|                                              |             |
|----------------------------------------------|-------------|
| 19.24 Release Series 1.5 (dora) . . . . .    | 2060        |
| 19.25 Release Series 1.4 (dylan) . . . . .   | 2060        |
| 19.26 Release Series 1.3 (danny) . . . . .   | 2060        |
| 19.27 Release Series 1.2 (denzil) . . . . .  | 2060        |
| 19.28 Release Series 1.1 (edison) . . . . .  | 2061        |
| 19.29 Release Series 1.0 (bernard) . . . . . | 2061        |
| 19.30 Release Series 0.9 (laverne) . . . . . | 2061        |
| <b>20 Indice</b>                             | <b>2063</b> |
| <b>21 Download della Documentazione</b>      | <b>2065</b> |
| <b>Indice</b>                                | <b>2067</b> |



---

## Build Rapida di un'Immagine con lo Yocto Project

---

### 1.1 Benvenuti!

Questo breve documento illustra la procedura per la creazione di un'immagine tipica utilizzando lo Yocto Project. Il documento spiega anche come configurare una build per un hardware specifico. Si userà lo Yocto Project per creare un sistema operativo embedded di riferimento chiamato Poky.

#### Nota

- Gli esempi in questo documento presuppongono l'uso di un sistema Linux nativo con una *versione supportata di una distribuzione Ubuntu Linux*. Se la macchina su cui si desidera utilizzare Yocto Project per creare un'immagine (*Build Host*) non è un sistema Linux nativo, è comunque possibile eseguire questi passaggi utilizzando un *container OCI* (tramite *Docker* o *Podman*).
- È possibile utilizzare la versione 2 di Windows Subsystem for Linux (WSL 2) per configurare un host di compilazione con Windows 10 o versioni successive, Windows Server 2019 o versioni successive. Per ulteriori informazioni, consultare la sezione *Setting Up to Use Windows Subsystem For Linux (WSL 2)* nel Manuale di Sviluppo dei Task di Yocto Project.

Per maggiori informazioni concettuali o di base sullo Yocto Project, consultare la sezione *Manuale Introduttivo e Concetti di Yocto Project*.

### 1.2 Distribuzione Linux Compatibile

Assicurarsi che il proprio *Build Host* soddisfi i seguenti requisiti:

- Almeno 140 GB di spazio libero su disco, ma una quantità maggiore consentirà di eseguire più build e di migliorare le prestazioni riutilizzando gli artefatti della build.

- Almeno 32 GB di RAM, sebbene per massimizzare le prestazioni di compilazione si raccomandi vivamente un host di compilazione moderno con la massima quantità di RAM e il maggior numero possibile di core CPU.
- Deve eseguire una distribuzione Linux supportata (ad esempio, versioni recenti di Fedora, openSUSE, CentOS, Debian o Ubuntu). Per un elenco delle distribuzioni Linux che supportano lo Yocto Project, consultare la sezione [Distribuzioni Linux Supportate](#) nel Manuale di Riferimento di Yocto Project. Per informazioni dettagliate sulla preparazione dell'host di compilazione, consultare la sezione [Preparing the Build Host](#) nel Manuale di Sviluppo dei Task di Yocto Project.
- Assicurarsi che le seguenti utility abbiano i seguenti numeri di versione minimi:
  - Git 2.22.0 o superiore
  - tar 1.28 o superiore
  - Python 3.9.0 o superiore
  - gcc 10.1 o superiore
  - GNU make 4.0 o superiore

Se l'host di compilazione non soddisfa tutti i requisiti di versione sopra indicati, si possono adottare delle misure per preparare il sistema in modo da poter comunque utilizzare lo Yocto Project. Consultare la sezione [Versioni richieste di Git, tar, Python, make e gcc](#) nel Manuale di Riferimento di Yocto Project per ulteriori informazioni.

### 1.3 Pacchetti dell'Host di Build

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione Linux Ubuntu o Debian supportata:

```
sudo apt-get install build-essential chrpath cpio debianutils diffstat file gawk ↵  
↵gcc git iputils-ping libacl1 libcrypt-dev locales python3 python3-git python3-  
↵jinja2 python3-pexpect python3-pip python3-subunit socat texinfo unzip wget xz-  
↵utils zstd
```

È inoltre necessario assicurarsi che sia abilitata la localizzazione `en_US.UTF-8`:

```
$ locale --all-locales | grep en_US.utf8
```

In caso contrario, è possibile riconfigurare il pacchetto `locales` per aggiungerla (richiede una shell interattiva):

```
$ sudo dpkg-reconfigure locales
```

#### Nota

- Se non si utilizza una shell interattiva, `dpkg-reconfigure` non funzionerà come previsto. Per aggiungere la localizzazione, è necessario modificare il file `/etc/locale.gen` per aggiungere/decommentare la localizzazione `en_US.UTF-8`. Un modo semplice per farlo come root è il seguente:

```
$ echo "en_US.UTF-8 UTF-8" >> /etc/locale.gen  
$ locale-gen
```

- Se il sistema di build ha installato il pacchetto `oss4-dev`, si potrebbero riscontrare errori di compilazione di QEMU a causa dell'installazione, da parte del pacchetto, di una propria versione personalizzata di `/usr/include/linux/soundcard.h` sul sistema Debian. Se ci si imbatte in questa situazione, provare una di queste soluzioni:

```
$ sudo apt build-dep qemu
$ sudo apt remove oss4-dev
```

#### **i** Nota

Per i requisiti dei pacchetti host su tutte le distribuzioni Linux supportate, consultare la sezione *Pacchetti Richiesti per l'Host di Build* nel Manuale di Riferimento di Yocto Project.

## 1.4 Installazione e utilizzo di bitbake-setup

Dopo aver completato le istruzioni di configurazione per la macchina, si deve ottenere una copia del tool `bitbake-setup` per configurare la distribuzione di riferimento di *Poky* sul proprio *build host*. Utilizzare i seguenti comandi per installare il tool in un ambiente virtuale Python:

```
$ python3 -m venv --clear ./bitbake-setup-venv
$ . ./bitbake-setup-venv/bin/activate
$ pip install bitbake-setup
```

#### **i** Nota

Il tool `bitbake-setup` è sviluppato e gestito nel repository di *BitBake*, quindi può essere utilizzato direttamente da lì:

```
$ git clone https://git.openembedded.org/bitbake ./bitbake
$ ./bitbake/bin/bitbake-setup ...
```

Configurare un ambiente di build con il seguente comando:

```
$ bitbake-setup init
```

Per default, questo creerà una directory principale nella directory corrente.

Se si preferisce configurare le build in una directory principale diversa, ad esempio `$HOME/bitbake-builds`, la si può impostare col comando `bitbake-setup settings`:

```
$ bitbake-setup settings set --global default top-dir-prefix $HOME
```

**i Nota**

Usare `bitbake-setup settings list` per ottenere una panoramica delle impostazioni.

`bitbake-setup init` è un programma interattivo per default e chiederà di prendere alcune decisioni. A seconda delle risposte, l'output potrebbe differire dagli esempi seguenti.

1. Scegliere una configurazione (ad esempio, `poky-master`):

```
Available Configuration Templates:
1. oe-nodistro-master   OpenEmbedded - 'nodistro' basic configuration
2. oe-nodistro-blacksail OpenEmbedded - 'nodistro' basic configuration,
↳ release 6.1 'blacksail' (supported until ...)
3. poky-master          Poky - The Yocto Project testing distribution
↳ configurations and hardware test platforms
4. poky-blacksail        Poky - The Yocto Project testing distribution
↳ configurations and hardware test platforms, release 6.1 'blacksail'
↳ (supported until ...)

Please select one of the above configurations by its number: 3
```

A seconda della scelta precedente, potrebbero essere richieste nuove opzioni per specificare ulteriormente quale configurazione utilizzare. Ad esempio:

```
Available bitbake configurations:
1. poky                  Poky - The Yocto Project testing distribution
2. poky-with-sstate      Poky - The Yocto Project testing distribution with
↳ internet sstate acceleration. Use with caution as it requires a completely
↳ robust local network with sufficient bandwidth.

Please select one of the above bitbake configurations by its number: 1
```

2. Scegliere una *MACHINE* target (ad esempio, `qemux86-64`):

```
Target machines:
1. machine/qemux86-64    x86-64 system on QEMU
2. machine/qemuarm64     ARMv8 system on QEMU
3. machine/qemuriscv64   RISC-V system on QEMU
4. machine/genericarm64  Arm64 SystemReady IR/ES platforms
5. machine/genericx86-64 x86_64 (64-bit) PCs and servers

Please select one of the above options by its number: 1
```

3. Scegliere una *DISTRO* (per esempio, `poky`):

Target distributions:

1. `distro/poky`                      Yocto Project Reference Distro
2. `distro/poky-altcfg`      Poky alternative with systemd as init manager
3. `distro/poky-tiny`        Poky alternative optimized for size

Please select one of the above options by its number: 1

#### 4. Scegliere un nome per la directory `setup`:

Enter setup directory name: [poky-master]

Premere Invio per lasciare il valore di default mostrato tra parentesi, oppure digitare un nome di directory personalizzato.

#### Nota

Se si preferisce eseguire il programma in modalità non interattiva, si può eseguire un comando come il seguente:

```
$ bitbake-setup init --non-interactive poky-master poky distro/poky machine/
→qemux86-64
```

Il comando `init` crea un nuovo `Setup` nella `top directory`. Il nome di default deriva dalla configurazione selezionata in precedenza.

Per le opzioni selezionate nell'esempio precedente, il nome sarebbe:

poky-master

Questa sarà la configurazione di esempio nelle sezioni seguenti.

Questa directory contiene:

- La directory **BitBake Build**, chiamata `build`. Successivamente, al termine della compilazione, questa directory conterrà tutti i file creati durante il processo.

Questa directory contiene anche un file `README`, che descrive la configurazione corrente e fornisce alcune istruzioni.

- I *layer*, nella directory `layers` servono per la build della distribuzione di riferimento di Poky.
- È presente anche una directory `config`, che rappresenta la configurazione corrente utilizzata per questo `setup`.

#### Nota

È inoltre possibile configurare manualmente la distribuzione di riferimento *Poky*. Per maggiori informazioni, consultare la sezione *Setting Up the Poky Reference Distro Manually* del Manuale di Sviluppo dei Task di Yocto Project.

## 1.5 Building dell'Immagine

Seguire i passaggi seguenti per compilare l'immagine. Il processo di compilazione (build) crea un'intera distribuzione Linux, inclusa la toolchain, a partire dai sorgenti.

### **i** Nota

- Se si lavora dietro un firewall e l'host di build non è configurato per i proxy, si potrebbero riscontrare problemi con il processo di build durante il recupero del codice sorgente (ad esempio, errori di fetcher o errori di Git).
- Se non si conoscono le impostazioni del proxy, consulta le risorse della propria infrastruttura di rete locale per ottenere queste informazioni. Un buon punto di partenza potrebbe essere anche controllare le impostazioni del browser web. Infine, si possono trovare maggiori informazioni nella pagina "[Working Behind a Network Proxy](#)" nello Yocto Project Wiki.

1. **Inizializzare il Build Environment:** Eseguire lo script di configurazione dell'ambiente `init-build-env` nella directory [BitBake build](#) per configurare l'ambiente di build [BitBake](#) sul proprio host:

```
$ source poky-master/build/init-build-env
Poky reference distro build
```

2. **Esaminare la Configurazione Corrente:** Quando si configura l'ambiente di compilazione [build], un file di configurazione denominato `toolcfg.conf` diventa disponibile in una sottocartella `conf/` della directory [BitBake build](#). Questo file viene modificato automaticamente dal tool da riga di comando `bitbake-config-build`. Con questo tool, si elencano i *frammenti di configurazione* attualmente abilitati:

```
$ bitbake-config-build list-fragments
```

Per questa configurazione, l'impostazione di default prevede l'utilizzo di due *Frammenti Nativi*:

- `distro/poky` imposta *DISTRO* a *Poky* (frammento *distro*).
- `machine/qemux86-64` imposta *MACHINE* a *qemux86-64* (frammento *machine*).

Questi valori dei frammenti corrispondono alle scelte effettuate durante l'esecuzione di `bitbake-setup init`.

### **i** Nota

Queste impostazioni configurano l'ambiente in modo simile a quanto precedentemente presente nel file di configurazione locale `local.conf`, che ora è in gran parte vuoto. Per configurare la build come in precedenza, consultare la sezione *Setting Up the Poky Reference Distro Manually* del Manuale di Sviluppo dei Task di Yocto Project.

La configurazione attuale non consente all'utente `root` di effettuare l'accesso. Poiché può essere utile per lo sviluppo, è possibile abilitare il frammento `core/yocto/root-login-with-empty-password`:

```
$ bitbake-config-build enable-fragment core/yocto/root-login-with-empty-
↳password
```

### **i** Nota

È possibile velocizzare significativamente la compilazione e proteggersi dagli errori del fetcher utilizzando i mirror *Cache di Shared State* e abilitando *Equivalenza degli Hash*. Ciò è rilevante solo se la rete e il server utilizzati possono scaricare questi artefatti più velocemente di quanto sarebbe possibile crearli.

Per utilizzare tali mirror, abilitare il frammento *core/yocto/sstate-mirror-cdn*:

```
$ bitbake-config-build enable-fragment core/yocto/sstate-mirror-cdn
```

Il server di equivalenza hash richiede il modulo Python websockets versione 9.1 o successiva. Debian GNU/Linux 12 (Bookworm) e versioni successive, Fedora, CentOS Stream 9 e versioni successive e Ubuntu 22.04 (LTS) e versioni successive dispongono tutte di un pacchetto sufficientemente recente. Le altre distribuzioni supportate devono ottenere il modulo da una fonte diversa dal proprio feed di pacchetti, ad esempio tramite `pip`. In alternativa, è possibile installare un tarball di *Buildtools* seguendo le istruzioni nella sezione *Versioni richieste di Git, tar, Python, make e gcc* del Manuale di Riferimento di Yocto Project.

3. **Avvio della Build:** Continuare col seguente comando per creare un'immagine del sistema operativo per il target, che in questo esempio è `core-image-sato`:

```
$ bitbake core-image-sato
```

Per informazioni sull'utilizzo del comando `bitbake`, consulta la sezione *BitBake* nel Manuale Introduttivo e Concetti di Yocto Project, oppure consultare *The BitBake Command* nel Manuale Utente di BitBake.

4. **Simulare l'Immagine con QEMU:** Una volta creata questa immagine, si può avviare QEMU, un "Quick EMUlator" incluso nello Yocto Project:

```
$ runqemu snapshot
```

Per ulteriori informazioni sull'esecuzione di QEMU, consultare il capitolo *Using the Quick EMUlator (QEMU)* nel Manuale di Sviluppo dei Task di Yocto Project.

5. **Uscita da QEMU:** Per uscire da QEMU, cliccare sull'icona di spegnimento oppure digitare `Ctrl-C` nella finestra di trascrizione di QEMU da cui è stato avviato il programma.

## 1.6 Personalizzazione della Build per un Hardware Specifico

Finora, tutto ciò che si è fatto è stato creare rapidamente un'immagine adatta solo all'emulazione. Questa sezione mostra come personalizzare la build per un hardware specifico aggiungendo un layer hardware all'ambiente di sviluppo di Yocto Project.

In generale, i layer sono repository che contengono set correlati di istruzioni e configurazioni che indicano allo Yocto Project cosa fare. Isolare i metadati correlati in layer specifici per funzionalità facilita lo sviluppo modulare e semplifica il riutilizzo dei metadati del layer.

**i Nota**

Per convenzione, i nomi dei layer iniziano con la stringa "meta-".

Seguire questi passaggi per aggiungere un *layer BSP*:

1. **Trovare un Layer:** Sono disponibili molti layer BSP. Il *layer index* può essere utilizzato per trovare tali layer. Questo esempio aggiunge il layer BSP *meta-raspberrypi*.

Innanzitutto, clonare il layer accanto agli altri layer:

```
git clone -b blacksail https://git.yoctoproject.org/meta-raspberrypi ../layers/
↪meta-raspberrypi
```

2. **Aggiungere il Layer al File di Configurazione dei Layer:** Prima di poterlo utilizzare, si deve aggiungere il layer e le sue dipendenze al file *build/conf/bblayers.conf*, che si trova nella directory *Build Directory* (*conf/*).

A tale scopo, si può utilizzare il comando `bitbake-layers add-layer`:

```
$ bitbake-layers add-layer ../layers/meta-raspberrypi
```

Si possono trovare maggiori informazioni sull'aggiunta di layer nella sezione *Aggiungere un Layer Utilizzando lo Script bitbake-layers*.

3. **Modificare la Configurazione per la Build su una Macchina Specifica:** La variabile *MACHINE* è definita dal frammento *machine/*. In questo esempio, il layer *meta-raspberrypi* fornisce la macchina *raspberrypi5*, quindi impostiamola come *MACHINE* utilizzata per la compilazione con `bitbake-config-build`:

```
$ bitbake-config-build enable-fragment machine/raspberrypi5
```

**i Nota**

Per ulteriori informazioni sulla configurazione della compilazione, consultare il passaggio "Esaminare la Configurazione Corrente" precedente.

La build *raspberrypi5* dipende da un firmware non libero (<https://github.com/RPi-Distro/firmware-nonfree>) che include la licenza *Synaptics*. Per ulteriori informazioni, consultare il documento *ipcompliance.md*. Aggiungere il valore *synaptics-killswitch* alla variabile *LICENSE\_FLAGS\_ACCEPTED*, nel file *build/conf/local.conf* della directory di build:

```
LICENSE_FLAGS_ACCEPTED = "synaptics-killswitch"
```

4. **Avviare la Build:** La configurazione è ora impostata per la build su Raspberry Pi 5. Avviare nuovamente la build:

```
$ bitbake core-image-sato
```



Il completamento di questi passaggi ha aggiunto il layer `meta-raspberrypi` all'ambiente [environment] di sviluppo di Yocto Project e lo ha configurato per la build per la macchina `raspberrypi5`.

#### Nota

I passaggi precedenti sono solo a scopo dimostrativo. Per tentare di creare un'immagine per la macchina `raspberrypi5`, si deve leggere il file `README.md` in `meta-raspberrypi`.

## 1.7 Creazione di un Proprio Layer Generico

Magari si ha un'applicazione o un insieme specifico di comportamenti da isolare. Si può creare un layer generico personalizzato utilizzando il comando `bitbake-layers create-layer`. Il tool automatizza la creazione dei layer impostando una sottocartella con un file di configurazione `layer.conf`, una sottocartella `recipes-example` contenente una ricetta `example.bb`, un file di licenza e un file `README`.

I seguenti comandi eseguono il tool per creare un layer denominato `meta-mylayer`:

```
$ bitbake-layers create-layer ../layers/meta-mylayer
NOTE: Starting bitbake server...
Add your new layer with 'bitbake-layers add-layer ../layers/meta-mylayer'
```

#### Nota

Per convenzione, i layer vengono posizionati uno accanto all'altro.

Per ulteriori informazioni sui layer e su come crearli, consultare la sezione *Creating Your Own Layer* nel Manuale di Sviluppo dei Task di Yocto Project.

## 1.8 Cosa Fare Ora?

Ora che c'è familiarità con lo Yocto Project, ci si potrebbe chiedere "E adesso?". Lo Yocto Project offre numerose fonti di informazione, tra cui il sito web, le pagine wiki e i manuali utente:

- **Sito Web:** Il [Sito Web di Yocto Project](#) fornisce informazioni di base, le build più recenti, le ultime notizie, la documentazione completa per lo sviluppo e l'accesso a una ricca Community di Sviluppatori di Yocto Project a cui è possibile partecipare.
- **Seminario Video:** I video [Introduction to the Yocto Project and BitBake, Part 1](#) e [Introduction to the Yocto Project and BitBake, Part 2](#) offrono un seminario video che introduce gli aspetti più importanti dello sviluppo di una distribuzione Linux embedded personalizzata con lo Yocto Project.
- **Manuale Introduttivo e Concetti di Yocto Project:** Il documento [Manuale Introduttivo e Concetti di Yocto Project](#) è un ottimo punto di partenza per conoscere lo Yocto Project. Questo manuale introduce lo Yocto Project e il suo ambiente di sviluppo. Il manuale fornisce anche informazioni concettuali su vari aspetti di Yocto Project.

- **Wiki di Yocto Project:** Lo [Yocto Project Wiki](#) fornisce ulteriori informazioni su come iniziare con lo Yocto Project, informazioni sulle release, pianificazione del progetto e informazioni sul controllo qualità.
  - **Mailing List di Yocto Project:** Le mailing list correlate offrono un forum per discussioni, invio di patch e annunci. Sono presenti diverse mailing list, raggruppate per argomento. Consultare la sezione [Mailing lists](#) nel Manuale di Riferimento di Yocto Project per un elenco completo delle mailing list di Yocto Project.
  - **Elenco Completo di Link e Altra Documentazione:** La sezione [Links and Related Documentation](#) nel Manuale di Riferimento di Yocto Project fornisce un elenco completo di tutti i link correlati e altra documentazione per gli utenti.
- 

The Yocto Project ®

<[docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org)>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.

---

### Cosa sarebbe stato utile sapere sullo Yocto Project

---

#### Nota

Prima di procedere con la lettura, si raccomanda di consultare la pagina [Technical Overview](#) la quale contiene le definizioni di molti dei termini qui menzionati. Inoltre, è importante considerare che alcune informazioni potrebbero non risultare chiare nell'immediato ma, con l'inizio dello sviluppo, rappresenteranno i dettagli da tenere maggiormente a portata di mano. Queste costituiscono le migliori pratiche per l'utilizzo di Yocto Project e vengono aggiornate regolarmente.

L'utilizzo di Yocto Project è relativamente semplice, *fino a quando non si verifica un problema*. Senza una comprensione approfondita del funzionamento del processo di compilazione, si rischierebbe di dover effettuare la risoluzione dei problemi alla cieca, come davanti a "una scatola nera [black box]". Di seguito vengono riportati alcuni elementi che gli utenti esperti avrebbero voluto conoscere prima di intraprendere la loro prima compilazione con Yocto Project. È possibile inviare feedback per proporre ulteriori suggerimenti.

1. **Utilizzare Git, non il download del tarball:** Con l'utilizzo di Git, il software viene aggiornato automaticamente con le correzioni dei bug grazie alle funzionalità intrinseche del sistema. Se invece si effettua il download del tarball, la gestione degli aggiornamenti rimarrà a carico esclusivo dell'utente.
2. **Conoscere l'indice dei layer:** Tutti i layer sono reperibili nel [layer index](#). I layer che hanno richiesto lo stato di compatibilità con Yocto Project (garanzia di continuità strutturale e test di conformità) sono disponibili alla pagina [Yocto Project Compatible Layers](#). In genere si consiglia di consultare prima l'indice dei layer compatibili e, nel caso in cui non si trovi il layer necessario, di verificare l'indice generale dei layer. L'indice dei layer è un elemento originario del progetto Open Embedded. Di conseguenza, tale indice non dispone della supervisione e dei test che Yocto Project fornisce per l'elenco dei layer compatibili, sebbene quest'ultimo contenga meno voci.

È opportuno sapere, quando si avvia una ricerca nell'indice dei layer, che non tutti i layer presentano lo stesso livello di maturità, convalida o usabilità. Inoltre, le ricerche non assegnano priorità ai risultati visualizzati. Non esiste un modo semplice per guidare l'utente nella scelta del layer più adatto alle proprie esigenze. Di conseguenza, si ricorre spesso a tentativi, alla consultazione delle mailing list o alla collaborazione con altri sviluppatori nelle apposite stanze virtuali per compiere le scelte migliori.

3. **Utilizzare layer BSP esistenti dei produttori di hardware quando possibile:** Intel, TI, NXP e altri forniscono informazioni su quali layer BSP utilizzare con i rispettivi chip. Questi layer hanno nomi come "meta-intel" o "meta-ti". Si raccomanda di evitare la creazione di layer da zero. In caso di utilizzo di chip personalizzati, è opportuno usare uno di questi layer come guida o modello e familiarizzare con il manuale *Manuale del Board Support Package (BSP) di Yocto Project*.
4. **Non inserire tutto all'interno di un unico layer:** Utilizzare layer diversi per separare logicamente le informazioni all'interno della build. A titolo di esempio, è possibile disporre di un layer BSP, un layer GUI, una configurazione di distribuzione (distro), un middleware o un'applicazione (es. "meta-filesystems", "meta-python", "meta-intel" e così via). L'inserimento dell'intera compilazione in un solo layer limita e complica la futura personalizzazione e il riutilizzo. Al contrario, l'isolamento delle informazioni nei singoli layer contribuisce a semplificare le personalizzazioni e il riutilizzo futuri.
5. **Mai modificare i layer core** (*BitBake*, *OpenEmbedded-Core (OE-Core)* ed eventualmente *meta-yocto*). Mai, in nessun caso. Al momento dell'aggiornamento al rilascio successivo, tutto il lavoro svolto andrà perduto. COMPLETAMENTE.\*\*
6. **Non farsi ingannare dai risultati di ricerca della documentazione:** La documentazione di Yocto Project viene aggiornata costantemente. Sfortunatamente, quando si utilizza Google per cercare concetti o termini relativi a Yocto Project, il motore di ricerca individua e restituisce sistematicamente versioni datate dei manuali. Ad esempio, la ricerca di uno specifico argomento su Google potrebbe portare a un risultato all'interno di un manuale di Yocto Project vecchio di diversi rilasci. Per avere la certezza di consultare la documentazione più recente di Yocto Project, si raccomanda di utilizzare il menù a tendina situato nella parte superiore di qualsiasi pagina.


Molti sviluppatori consultano il manuale *All-in-one 'Mega' Manual* per trovare un concetto o un termine effettuando una ricerca nell'intera pagina. Questo manuale è una concatenazione del set di manuali principali di Yocto Project. Pertanto, una semplice ricerca testuale tramite Ctrl+F all'interno di questo documento mostra tutte le corrispondenze per il termine o il concetto desiderato. Una volta individuata l'area di interesse, è possibile visualizzare il manuale effettivo, se lo si desidera. È inoltre possibile utilizzare la barra di ricerca presente nel menu o nel pannello di navigazione sinistro.

7. **Comprendere i concetti di base del funzionamento del sistema di build (il workflow):** La comprensione del flusso di lavoro di Yocto Project è fondamentale, poiché permette sia di individuare il punto esatto in cui si verificano le anomalie, sia di capire le cause dell'interruzione della compilazione. Il flusso di lavoro si suddivide nelle seguenti fasi:
  1. Fetch - recupero del codice sorgente
  2. Extract - estrazione dei sorgenti
  3. Patch - applicazione delle patch per la correzione di bug e nuove funzionalità
  4. Configure - impostazione delle specifiche dell'ambiente
  5. Build - compilazione e collegamento (linking)

6. Install - copia dei file nelle directory di destinazione

7. Package - pacchettizzazione dei file per l'installazione

Durante la fase di "fetch", potrebbe verificarsi l'impossibilità di reperire il codice. Durante la fase di "extract", è probabile che si riscontri un archivio zip non valido o un problema analogo. In altri termini, la funzione di una determinata parte del flusso di lavoro fornisce un'indicazione su cosa potrebbe non funzionare correttamente.



8. **Generazione del grafo delle dipendenze:** È possibile generare un grafo delle dipendenze per visualizzare le relazioni tra ricette (recipes), attività (tasks) e obiettivi (targets). Per generare questo grafo, si utilizza l'opzione "-g" con BitBake. Quando si avvia una compilazione e questa si interrompe, potrebbero comparire pacchetti sconosciuti o inseriti dal sistema senza un motivo apparente. Il grafo delle dipendenze permette di chiarire tale ambiguità. Per approfondire l'argomento e comprendere come generare i grafi, si rimanda alla sezione [Generating Dependency Graphs](#) del Manuale Utente di BitBake.

9. **Decodifica dei nomi "magici" delle cartelle in tmp/work:** Il sistema di build esegue il recupero, l'estrazione, la pre-elaborazione e la compilazione. In caso di errore, il sistema segnala direttamente il percorso di una cartella in cui risiedono i file temporanei (build/tmp) e i pacchetti risultanti dalla compilazione. Per un esempio dettagliato di questo processo, si veda l' [esempio](#), sebbene sia basato su un rilascio precedente di Yocto Project.

Quando si esegue una compilazione, è possibile utilizzare l'opzione da riga di comando "-u" di BitBake per specificare un'interfaccia utente di visualizzazione del grafo delle dipendenze (ad es. knotty, ncurses o taskexp), facilitando così la comprensione delle dipendenze di compilazione.

10. **Compilazione di elementi diversi dalle sole immagini:** È possibile compilare ed eseguire una specifica attività [task] per un determinato pacchetto (incluso devshell) o persino una singola ricetta. Quando si inizia a utilizzare Yocto Project, le istruzioni contenute in [Build Rapida di un'Immagine con lo Yocto Project](#) mostrano come creare un'immagine e poi eseguirla o effettuarne il flash. Tuttavia, è consentito compilare anche una singola ricetta. Pertanto, se una dipendenza o una ricetta non funziona, è sufficiente eseguire il comando "bitbake foo" dove "foo" è il nome della specifica ricetta. Man mano che si acquisisce maggiore esperienza con Yocto Project, e nel caso in cui le compilazioni falliscano, può essere utile verificare che la fase di fetch funzioni correttamente. Ecco alcuni link utili: [Using a Development Shell](#) per informazioni su come compilare ed eseguire un task specifico con devshell. Inoltre il [manuale SDK mostra come compilare una specifica ricetta](#).

11. **Una definizione ambigua: Pacchetto contro Ricetta:** Una ricetta contiene le istruzioni che il sistema di compilazione utilizza per creare i pacchetti. Ricette e pacchetti rappresentano la differenza tra la fase iniziale (front end) e il risultato finale del processo di compilazione.

Come menzionato, il sistema di compilazione [build] prende la ricetta e crea i pacchetti in base alle istruzioni in essa contenute. I pacchetti risultanti sono correlati all'elemento principale che la ricetta sta compilando, ma costituiscono parti diverse (pacchetti) della compilazione (ovvero il pacchetto principale, quello di documentazione, il pacchetto con i simboli di debug, quello con le utilità separate e così via). Il sistema suddivide i pacchetti in modo da evitare l'installazione di componenti non desiderati o non necessari, il che rappresenta un vantaggio significativo quando si sviluppa per piccoli dispositivi in ambito embedded e IoT.

12. **È importante conoscere e sapere cosa è contenuto nel filesystem di root.**

13. **Creazione di una propria ricetta di immagine:** Esistono diversi modi per creare una ricetta di immagine personalizzata. Si consiglia di creare una propria ricetta di immagine anziché estenderne una esistente. La scrittura di una ricetta di immagine è un'operazione semplice e immediata. Si ribadisce l'indicazione di non tentare l'estensione di una ricetta di immagine esistente, bensì di crearne una propria fin dall'inizio per procedere correttamente.

14. **Di seguito viene riportato l'elenco delle competenze fondamentali necessarie per uno sviluppatore di sistemi. È fondamentale essere in grado di:**

- gestire i proxy aziendali
- aggiungere un pacchetto a un'immagine
- comprendere la differenza tra una ricetta e un pacchetto
- configurare un pacchetto in autonomia e capire l'utilità di tale procedura
- identificare i pacchetti creati da una ricetta
- identificare i file contenuti in un pacchetto
- identificazione i file contenuti in un'immagine
- aggiungere un server SSH a un'immagine (abilitazione del trasferimento file sul target)
- conoscere l'anatomia di una ricetta
- conoscere la creazione e l'utilizzo dei layer
- cercare ricette (con lo [OpenEmbedded Layer index](#))
- Capire la differenza tra le impostazioni MACHINE e DISTRO
- cercare e usare il BSP (machine) corretto per l'hardware in uso
- cercare esempi di funzionalità DISTRO e individuare la loro corretta collocazione
- capire la pipeline dei task e l'esecuzione dei singoli task
- capire devtool e la semplificazione del flusso di lavoro
- migliorare la velocità di build tramite download e cache di stato condivisi [shared]
- generare e comprendere un grafo delle dipendenze
- generare e comprendere l'ambiente BitBake

- configurare un Extensible SDK per lo sviluppo di applicazioni

15. A seconda degli interessi principali relativi a Yocto Project, si consiglia la lettura dei seguenti testi:

- **Consultare il Manuale di Sviluppo dei Task di Yocto Project:** Questo manuale contiene informazioni sulle procedure raggruppate per aiutare nella configurazione, nel lavoro con i layer, nella personalizzazione delle immagini, nella scrittura di nuove ricette, nell'utilizzo delle librerie e nell'uso di QEMU. Le informazioni sono basate su task e coprono per intero a Yocto Project. Si veda la sezione dedicata *Manuale di Sviluppo dei Task di Yocto Project*.
- **Consultare il Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK):** Questo manuale descrive l'utilizzo sia dell'SDK standard sia dell'SDK estensibile, impiegati principalmente per lo sviluppo di applicazioni. Il manuale *Using the Extensible SDK* fornisce inoltre esempi di flussi di lavoro che utilizzano devtool. Per ulteriori informazioni, si veda la sezione *Using devtool in Your SDK Workflow*.
- **Studio dello Sviluppo del Kernel:** Per comprendere il funzionamento del kernel e dei kernel Linux Yocto, si rimanda alla guida specifica *Manuale di Sviluppo del Kernel Linux di Yocto Project*. Questo manuale fornisce informazioni su come applicare patch al kernel, modificare le ricette del kernel e configurare il kernel stesso.
- **Studio dei Board Support Package (BSP):** Per informazioni sui BSP, si rimanda al manuale dedicato *Manuale del Board Support Package (BSP) di Yocto Project*. Tale manuale fornisce anche un esempio di flusso di lavoro per la creazione di un BSP. Si veda la sezione specifica *Manuale del Board Support Package (BSP) di Yocto Project*.
- **Studio di Toaster:** Toaster è un'interfaccia web per il sistema di build OpenEmbedded di Yocto Project. Se vi è interesse nell'utilizzo di questo tipo di interfaccia per la creazione di immagini, si rimanda al manuale di Toaster *Manuale Utente di Toaster*.
- **Scoprire l'estensione per VSCode:** L'estensione [Yocto Project BitBake](#) per l'IDE Visual Studio Code fornisce funzionalità di linguaggio e comandi per lavorare con Yocto Project. Se vi è interesse nell'utilizzo di questa estensione, è possibile visitarne la [pagina sul marketplace](#).
- **Tenere a portata di mano il Manuale di Riferimento di Yocto Project:** A differenza degli altri manuali di Yocto Project, questo testo è composto da materiale adatto alla consultazione piuttosto che a procedure passo-passo. È possibile ottenere dettagli sulla build, un'analisi approfondita dell'integrazione dei componenti nell'ambiente di sviluppo di Yocto Project, informazioni su dettagli tecnici, indicazioni sulla migrazione a versioni più recenti di Yocto Project e materiale di riferimento su struttura delle directory, classi e task. *Yocto Project Reference Manual* contiene inoltre un glossario completo delle variabili utilizzate all'interno di Yocto Project.

---

The Yocto Project ®

<docs@lists.yoctoproject.org>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo `docs@lists.yoctoproject.org` o di accedere su [Libera Chat](#) al canale #yocto.



---

## Transizione a un ambiente personalizzato per lo sviluppo di sistemi

---

### Nota

È stata completata la documentazione *Build Rapida di un'Immagine con lo Yocto Project* ed è stato visto il documento *Cosa sarebbe stato utile sapere sullo Yocto Project*, quest'ultimo contenente informazioni importanti apprese da altri utenti. Si è ben preparati. Ma ora che si sta iniziando il proprio progetto, non è così semplice capire cosa fare e la documentazione può sembrare scoraggiante. Abbiamo raccolto alcuni suggerimenti per aiutare ad iniziare.

1. **Fare un elenco del processore, della scheda target, delle tecnologie e delle funzionalità che faranno parte del progetto.** Si troveranno dei layer con ricette e altri metadati che supportano questi elementi e si dovranno aggiungerli alla configurazione. (Vedere il punto #3)
2. **Configurare il supporto per la scheda.** Anche se si usa un proprio hardware, potrebbe essere più semplice iniziare con una scheda target esistente che utilizza lo stesso processore o almeno la stessa architettura del proprio hardware. Sapere che la scheda ha già un Board Support Package (BSP) funzionante all'interno del progetto aiuterà a familiarizzare più facilmente con i concetti del progetto.
3. **Trovare e acquistare il miglior BSP per la propria scheda target.** Usare lo [Yocto Project Compatible Layers](#) o anche [OpenEmbedded Layer Index](#) per trovare e acquistare il miglior BSP per la propria scheda target. I BSP dell'indice dei layer di Yocto Project vengono regolarmente validati. Il posto migliore per ottenere il primo BSP è il produttore del silicio o il fornitore della scheda: possono indicarti i loro BSP più qualificati. In generale, per i silicio Intel si usa `meta-intel`, per Texas Instruments si usa `meta-ti` e così via. Scegliere un BSP testato con la stessa versione di Yocto Project scaricata. Si tenga che alcuni BSP potrebbero non essere immediatamente supportati sull'ultima versione, ma lo saranno in seguito.

Si consiglia di iniziare con la specifica di build fornita da *Poky* (la distribuzione embedded di riferimento) per poi aggiungere i layer selezionati. Queste le informazioni *sull'aggiunta dei layer*.

4. **Modifica della configurazione in base ai layer scelti.** Ad esempio, supponiamo che sia stato scelto un tipo di macchina e aggiunto il layer BSP corrispondente. Si dovrà quindi modificare il valore della variabile *MACHINE* nella configurazione (utilizzando il frammento *machine/*) in modo che punti a quello stesso tipo di macchina. Potrebbero esserci anche altre impostazioni specifiche del layer da modificare. Ogni layer ha un documento README consultabile per questo tipo di informazioni sull'utilizzo.
5. **Creazione di un nuovo layer per ricette e metadati personalizzati.** L'operazione viene eseguita tramite il comando `bitbake-layers create-layer`. Il tool `bitbake-layers` offre inoltre comandi aggiuntivi per la gestione dei layer. Consultare la sezione *Creating Your Own Layer*.
6. **Crea il layer per il BSP che si intende utilizzare.** Non è frequente dover creare un intero BSP da zero, a meno che non si disponga di un dispositivo *davvero* speciale. Anche se si utilizza un BSP esistente, *creare il proprio layer per il BSP*. Ad esempio, data una macchina basata su x86 a 64 bit, si copia la definizione `conf/intel-corei7-64` e si assegna alla macchina un nome appropriato (si pensi al nome della scheda, non al nome del prodotto). La configurazione del layer deve dipendere dal layer `meta-intel` (o almeno, che, `meta-intel` rimanga nel file `build/conf/bblayers.conf`). Ora si possono inserire le impostazioni BSP personalizzate nel layer e riutilizzarle per diverse applicazioni.
7. **La scrittura di una ricetta personalizzata è necessaria per compilare software di supporto non ancora disponibile.** Tale operazione risulta fondamentale per il software applicativo personalizzato da eseguire sul dispositivo. Scrivere nuove ricette è un processo di perfezionamento. Si inizia assicurando che ogni fase del processo di compilazione funzioni correttamente, a partire dal recupero dei dati fino al packaging. Successivamente, si esegue il software sul dispositivo target e lo si perfeziona ulteriormente secondo necessità. Consultare la sezione *Scrivere una Nuova Ricetta* nel Manuale di Sviluppo dei Task di Yocto Project per ulteriori informazioni.
8. **Ora si è pronti per creare una ricetta per l'immagine.** Esistono diversi modi per farlo. Tuttavia, è fortemente consigliato creare una ricetta per l'immagine personalizzata: non tentare di aggiungere contenuti a ricette esistenti. Creare ricette per le immagini è semplice e in genere si desidera personalizzarne completamente il contenuto.
9. **Compilare l'immagine e perfezionala.** Aggiungere ciò che manca e correggere eventuali problemi, sfruttando la conoscenza del *workflow* per identificare le possibili cause dei problemi.
10. **Valutare la possibilità di creare una distribuzione personalizzata.** Quando si raggiunge un certo livello di personalizzazione, considerare la creazione di una distribuzione personalizzata anziché utilizzare quella di riferimento predefinita.

Le impostazioni della distribuzione definiscono il back-end di creazione dei pacchetti (ad esempio rpm o altro), il feed dei pacchetti e, eventualmente, la soluzione di aggiornamento. Dovresti creare la tua distribuzione in un nuovo layer che eredita da *Poky* ma sovrascrivendo ciò che deve essere modificato per la tua distribuzione. Se ti ritrovi ad aggiungere molta configurazione al tuo file `build/conf/local.conf` oltre ai percorsi e ad altre tipiche impostazioni locali, è il momento di *considerare la creazione di una propria distribuzione*.

È possibile aggiungere specifiche di prodotto che personalizzano la distribuzione, se necessario, in altri layer. È inoltre possibile aggiungere altre funzionalità specifiche per il prodotto. Tuttavia, per aggiornare la di-

sistribuzione, e non i singoli prodotti, è necessario aggiornare la funzionalità di distribuzione tramite il layer corrispondente.

11. **Congratulazioni! Si è sulla buona strada.** Benvenuto nella community di Yocto Project.

---

The Yocto Project ®

[<docs@lists.yoctoproject.org>](mailto:docs@lists.yoctoproject.org)

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.



---

### Manuale Introduttivo e Concetti di Yocto Project

---

Benvenuti nel Manuale Introduttivo e Concetti di Yocto Project! Questo manuale presenta Yocto Project fornendo concetti, una panoramica del software, le migliori pratiche (BKM) e qualsiasi altra informazione introduttiva di alto livello adatta a un nuovo utente di Yocto Project.

Ecco cosa c'è in questo manuale:

- *Introduzione a Yocto Project*: Questo capitolo fornisce un'introduzione a Yocto Project. Si vedranno le caratteristiche e le sfide di Yocto Project, il modello a layer, i componenti e i tool, i metodi di sviluppo, la distribuzione di riferimento *Poky*, il flusso di lavoro di *OpenEmbedded Build System* e alcuni termini base di Yocto.
- *L'Ambiente di Sviluppo di Yocto Project*: Questo capitolo illustrerà l'ambiente di sviluppo di Yocto Project. In questo si conoscerà l'open source, gli host di sviluppo, i repository del codice sorgente di Yocto Project, i flussi di lavoro che utilizzano Git e Yocto Project, un'introduzione a Git e informazioni sulle licenze.
- *Concetti di Yocto Project*: Questo capitolo presenta diversi concetti relativi a Yocto Project. Si troveranno informazioni concettuali su componenti, sviluppo, toolchain cross-compilation e altro ancora.

Questo manuale non include quanto segue:

- *Istruzioni Dettagliate per i Task di Sviluppo*: Le procedure dettagliate si trovano in altri manuali all'interno della documentazione di Yocto Project. Ad esempio, il manuale *Manuale di Sviluppo dei Task di Yocto Project* fornisce esempi su come eseguire diversi task di sviluppo. Un altro esempio è il manuale *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)*, che contiene istruzioni dettagliate su come installare un SDK, utilizzato per sviluppare applicazioni per l'hardware di destinazione [target].
- *Materiale di Riferimento*: Questo tipo di materiale si trova in un apposito manuale di riferimento. Ad esempio, le variabili di sistema sono documentate nel file *Yocto Project Reference Manual*. Un altro esempio è il file *Manuale del Board Support Package (BSP) di Yocto Project*, che contiene informazioni di riferimento sui BSP (Business Support Package).


- *Informazioni pubbliche dettagliate non specifiche di Yocto Project:* Ad esempio, informazioni esaustive su come utilizzare il Source Control Manager Git sono reperibili più facilmente tramite ricerche su Internet e la documentazione ufficiale di Git, piuttosto che attraverso la documentazione di Yocto Project.

## 4.1 Introduzione a Yocto Project

### 4.1.1 Cos'è Yocto Project?

Yocto Project è un progetto collaborativo open source che aiuta gli sviluppatori a creare sistemi personalizzati basati su Linux, progettati per prodotti embedded indipendentemente dall'architettura hardware del prodotto. Yocto Project fornisce un set di strumenti flessibile e un ambiente di sviluppo che consente agli sviluppatori di dispositivi embedded di tutto il mondo di collaborare attraverso tecnologie, stack software, configurazioni e best practice condivise per creare queste immagini Linux personalizzate.

Migliaia di sviluppatori in tutto il mondo hanno scoperto che Yocto Project offre vantaggi sia nello sviluppo di sistemi che di applicazioni, sia in termini di archiviazione e gestione, sia per quanto riguarda le personalizzazioni in termini di velocità, ingombro e utilizzo della memoria. Il progetto è uno standard per la fornitura di stack software embedded. Il progetto consente la personalizzazione del software e lo scambio di build per diverse piattaforme hardware, nonché stack software che possono essere mantenuti e scalati.



Il resto di questa sezione illustra i vantaggi e le sfide legate a Yocto Project.

### Caratteristiche

Ecco le caratteristiche e i vantaggi di Yocto Project:

- *Ampiamente Adottato nel Settore:* Molti produttori di semiconduttori, sistemi operativi, software e servizi adottano e supportano Yocto Project nei loro prodotti e servizi. Per una panoramica della community di Yocto Project e delle aziende coinvolte, consultare le schede "COMMUNITY" e "ABOUT" nella pagina home di [Yocto Project](#).
- *Indipendente dall'Architettura:* Yocto Project supporta Intel, ARM, MIPS, AMD, PPC, RISC-V e altre architetture. La maggior parte dei Original Design Manufacturers (ODM) [produttori di design originali], dei Operating System Vendors (OSV) [fornitori di sistemi operativi] e dei produttori di chip creano e forniscono BSP che supportano il loro hardware. Se si dispone di silicio personalizzato, è possibile creare un BSP che

supporti tale architettura. Consultare la documentazione *Architetture e Funzionalità Supportate da Yocto Project* per i dettagli sul livello di supporto per alcune di queste architetture.

Oltre a un ampio supporto architetturale, Yocto Project supporta pienamente una vasta gamma di dispositivi emulati da Quick EMUlator (QEMU).

- *Trasferimento Semplificato di Immagini e Codice:* L'output di Yocto Project può essere facilmente trasferito tra architetture senza dover passare a nuovi ambienti di sviluppo. Inoltre, se è stato utilizzato Yocto Project per creare un'immagine o un'applicazione e non si è più in grado di supportarla, i fornitori commerciali di Linux elencati su <https://www.yoctoproject.org/members/> e <https://www.yoctoproject.org/about/participants/> potrebbero prenderla in carico e fornire supporto continuo.
- *Flessibilità:* Le aziende utilizzano Yocto Project in molti modi diversi. Un esempio è la creazione di una distribuzione Linux interna come base di codice che l'azienda può utilizzare in più gruppi di prodotto. Attraverso la personalizzazione e il layering, un gruppo di progetto può sfruttare la distribuzione Linux di base per creare una distribuzione adatta alle proprie esigenze di prodotto.
- *Ideale per dispositivi Embedded e IoT con Risorse Limitate:* A differenza di una distribuzione Linux completa, con Yocto Project è possibile creare esattamente ciò di cui si ha bisogno per i dispositivi embedded. È sufficiente aggiungere il supporto per le funzionalità o i pacchetti strettamente necessari al dispositivo. Per i dispositivi dotati di display, è possibile utilizzare componenti di sistema disponibili come X11, Wayland, GTK+, Qt, Clutter e SDL (tra gli altri) per creare un'esperienza utente ricca e intuitiva. Per i dispositivi sprovvisti di display o per i quali si desidera utilizzare framework UI alternativi, è possibile scegliere di non compilare questi componenti.
- *Complete Funzionalità della Toolchain:* Le toolchain per le architetture supportate sono sufficienti per la maggior parte dei casi d'uso. Tuttavia, se l'hardware supporta funzionalità non incluse in una toolchain standard, è possibile personalizzarla facilmente specificando parametri di configurazione specifici della piattaforma. Inoltre, qualora fosse necessario utilizzare una toolchain di terze parti, i meccanismi integrati in Yocto Project lo consentono.
- *Meccanismo al costo delle Politiche:* Concentrarsi sul meccanismo piuttosto che sulle politiche garantisce la libertà di definire le politiche in base alle esigenze del proprio progetto, anziché adottare decisioni imposte da un fornitore di software di sistema.
- *Utilizza un Modello a Layer:* L'*infrastruttura a layer* di Yocto Project raggruppa le funzionalità correlate in bundle separati. È possibile aggiungere gradualmente queste funzionalità raggruppate al progetto, a seconda delle necessità. L'utilizzo dei layer per isolare e raggruppare le funzionalità riduce la complessità e la ridondanza del progetto, consente di estendere facilmente il sistema, apportare personalizzazioni e mantenere le funzionalità organizzate.
- *Supporta le Build Parziali:* È possibile compilare e ricompilare singoli pacchetti secondo necessità. Yocto Project realizza ciò tramite il suo schema di cache di stato shared (sstate) (*Cache di Shared State*). La possibilità di compilare ed eseguire il debug dei componenti singolarmente semplifica lo sviluppo del progetto.
- *Rilasci Secondo una Pianificazione Rigorosa:* I rilasci principali avvengono con una *cadenza semestrale*, prevedibilmente a ottobre e aprile. Gli ultimi due rilasci includono aggiornamenti per risolvere vulnerabilità e punti deboli comuni. Questa prevedibilità è fondamentale per i progetti basati su Yocto Project e consente ai team di sviluppo di pianificare le attività.

- *Un Ricco Ecosistema di Individui e Organizzazioni:* Per i progetti open source, il valore della community è molto importante. Forum di supporto, competenze e sviluppatori attivi che continuano a far progredire Yocto Project sono facilmente reperibili.
- *Riproducibilità Binaria:* Yocto Project permette di essere molto precisi riguardo alle dipendenze e raggiunge percentuali molto elevate di riproducibilità binaria (ad esempio, 99,8% per `core-image-minimal`). Quando le distribuzioni non specificano quali pacchetti includere e in quale ordine per supportare le dipendenze, altri sistemi di build possono includere pacchetti in modo arbitrario.
- *Manifesto di Licenza:* Yocto Project fornisce un *license manifest* da esaminare da parte di chi ha bisogno di tenere traccia dell'utilizzo delle licenze open source (ad esempio, i team legali).

### Sfide

Ecco alcune sfide che si potrebbero incontrare durante lo sviluppo con Yocto Project:

- *Curva di Apprendimento Ripida:* Yocto Project presenta una curva di apprendimento ripida e offre molti modi diversi per svolgere attività simili. Può essere difficile scegliere tra questi metodi.
- *Comprendere Quali Modifiche Apportare al Progetto Richiede Ricerca:* Oltre alla semplice fase di tutorial, comprendere quali modifiche apportare al progetto specifico può richiedere una notevole quantità di ricerca e approfondimento. Per informazioni che aiutino a passare dalla fase di prova di Yocto Project al suo utilizzo per il progetto, consultare i documenti "*Cosa sarebbe stato utile sapere sullo Yocto Project*" e "*Transizione a un ambiente personalizzato per lo sviluppo di sistemi*" sul sito web di Yocto Project.
- *Il Flusso di Lavoro del Progetto Potrebbe Risultare Complesso:* Il *workflow di Yocto Project* potrebbe risultare complesso per chi è abituato allo sviluppo software tradizionale per desktop e server. In un ambiente di sviluppo desktop, esistono meccanismi per scaricare e installare facilmente nuovi pacchetti, che in genere sono binari precompilati da server accessibili tramite Internet. Con Yocto Project, è necessario modificare la configurazione e ricompilare il progetto per aggiungere pacchetti aggiuntivi.
- *Lavorare in un Ambiente di Cross-build può Risultare Insolito:* Quando si sviluppa codice da eseguire su una piattaforma target, la compilazione, l'esecuzione e il test sulla piattaforma stessa possono essere più veloci rispetto all'esecuzione di una build BitBake su un host di sviluppo e al successivo deployment dei binari sulla piattaforma target per il test. Sebbene Yocto Project supporti gli strumenti di sviluppo sulla piattaforma target, è comunque necessario integrare le modifiche nell'ambiente di build di Yocto Project. Yocto Project supporta un approccio intermedio che prevede di apportare modifiche al sistema di sviluppo all'interno dell'ambiente BitBake e quindi di distribuire sul sistema target solo i pacchetti aggiornati.

L'*OpenEmbedded Build System* di Yocto Project produce pacchetti in formati standard (ad esempio RPM, DEB e/o IPK). Se nell'immagine è stata inclusa la *gestione dei pacchetti in fase di runtime*, si possono distribuire questi pacchetti nel sistema in esecuzione sul sistema target utilizzando le utilità corrispondenti, come `rpm/dnf`, `dpkg/apt` o `opkg`.

- *I Tempi di Compilazione Iniziali Possono Essere Significativi:* Tempi di compilazione iniziali lunghi sono purtroppo inevitabili a causa dell'elevato numero di pacchetti che vengono inizialmente compilati da zero per un sistema Linux completamente funzionante. Una volta completata la compilazione iniziale, tuttavia, il meccanismo di cache a shared-state (sstate) utilizzato da Yocto Project impedisce al sistema di ricompilare i pacchetti che non sono stati "modificati" dall'ultima compilazione. Il meccanismo sstate riduce significativamente i tempi per le compilazioni successive.



### 4.1.2 Il Modello a Layer di Yocto Project

Il Modello a Layer di Yocto Project è un modello di sviluppo per la creazione di applicazioni Linux embedded e IoT che distingue Yocto Project da altri semplici sistemi di build. Il modello a layer supporta simultaneamente la collaborazione e la personalizzazione. I layer sono repository che contengono insiemi di istruzioni correlate che indicano all'*OpenEmbedded Build System* cosa fare. È possibile collaborare, condividere e riutilizzare i layer.

I layer possono contenere modifiche a istruzioni o impostazioni precedenti in qualsiasi momento. Questa potente capacità di override consente di personalizzare i layer collaborativi o della community precedentemente forniti per adattarli ai requisiti del proprio prodotto.

Si utilizzano layer diversi per separare logicamente le informazioni nella build. Ad esempio, si potrebbero avere layer per BSP, GUI, configurazione della distribuzione, middleware o applicazione. Inserire l'intera build in un unico layer limita e complica la personalizzazione e il riutilizzo futuri. Isolare le informazioni in layer, d'altra parte, aiuta a semplificare le personalizzazioni e il riutilizzo futuri. Potrebbe essere allettante mantenere tutto in un unico layer quando si lavora su un singolo progetto. Tuttavia, maggiore è la modularità dei metadati, più facile sarà gestire le modifiche future.

#### Nota

- Utilizzare i layer BSP (Board Support Package) dei produttori di semiconduttori quando possibile.
- Familiarizzare con i [Yocto Project Compatible Layers](#) o con l'[OpenEmbedded Layer Index](#). Quest'ultimo contiene più layer, ma sono meno universalmente validati.
- I layer supportano l'inclusione di tecnologie, componenti hardware e software. La dicitura *Yocto Project Compatible* fornisce un layer minimo di standardizzazione che contribuisce a un solido ecosistema. La dicitura "YP Compatible" viene applicata a prodotti e componenti software appropriati, come BSP, altri layer compatibili con OpenEmbedded e progetti open source correlati, consentendo al produttore di utilizzare i badge e gli elementi di branding di Yocto Project.

Per illustrare come i layer vengano utilizzati per mantenere la modularità, consideriamo le personalizzazioni della macchina. Questo tipo di personalizzazioni risiede in genere in un layer speciale, anziché in uno generale, chiamato BSP Layer. Inoltre, le personalizzazioni della macchina dovrebbero essere isolate dalle ricette e dai metadati che supportano un nuovo ambiente GUI, ad esempio. Questa situazione crea un paio di layer: uno per le configurazioni della macchina e uno per l'ambiente GUI. È importante comprendere, tuttavia, che il layer BSP può comunque aggiungere modifiche specifiche della macchina alle ricette all'interno del layer dell'ambiente GUI senza inquinare il layer GUI stesso con tali modifiche specifiche della macchina. È possibile ottenere questo risultato tramite una ricetta che è un file di append BitBake (`.bbappend`), descritto più avanti in questa sezione.

**i Nota**

Per informazioni generali sulla struttura dei layer BSP, consultare il *Manuale del Board Support Package (BSP) di Yocto Project*.

*Source Directory* contiene sia layer generali che layer BSP già pronti all'uso. È possibile identificare facilmente i layer inclusi in una release di Yocto Project nella directory dei sorgenti tramite i loro nomi. I layer hanno in genere nomi che iniziano con la stringa `meta-`.

**i Nota**

Non è obbligatorio che il nome di un layer inizi con il prefisso `meta-`, ma è uno standard comunemente accettato nella community di Yocto Project.

Ad esempio, se si esamina la [vista ad albero](#) del repository `openembedded-core`, si vedranno diversi layer: `meta`, `meta-skeleton` e `meta-selftest`. Ciascuno di questi repository rappresenta un layer distinto.

Per le procedure su come creare layer, consultare la sezione "[Comprendere e Creare i Layer](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

### 4.1.3 Componenti e Tool

Yocto Project utilizza una serie di componenti e strumenti impiegati dal progetto stesso, dagli sviluppatori del progetto e da coloro che utilizzano Yocto Project. Questi componenti e strumenti sono progetti open source e metadati separati dalla distribuzione di riferimento (*Poky*) e il *OpenEmbedded Build System*. La maggior parte dei componenti e degli strumenti viene scaricata separatamente.

Questa sezione fornisce una breve panoramica dei componenti e degli strumenti associati a Yocto Project.

#### Strumenti di Sviluppo

Ecco gli strumenti che aiutano a sviluppare immagini e applicazioni utilizzando Yocto Project:

- *devtool*: Questo strumento da riga di comando è disponibile come parte dell'SDK estensibile (eSDK) e ne rappresenta il fondamento. Si può utilizzare `devtool` per compilare, testare e impacchettare il software all'interno dell'eSDK. Puoi utilizzare lo strumento per integrare facoltativamente il lavoro in un'immagine creata dal sistema di build OpenEmbedded.

Il comando `devtool` utilizza una serie di sottocomandi che consentono di aggiungere, modificare e aggiornare le ricette. Come nel sistema di build OpenEmbedded, le "ricette" rappresentano pacchetti software all'interno di `devtool`. Quando si utilizza `devtool add`, viene creata automaticamente una ricetta. Quando si utilizza `devtool modify`, viene utilizzata la ricetta esistente specificata per determinare dove reperire il codice sorgente e come applicarvi le patch. In entrambi i casi, viene configurato un ambiente in modo che, durante la compilazione della ricetta, venga utilizzato un albero dei sorgenti sotto il proprio controllo, consentendo di apportare modifiche al codice sorgente a piacimento. Per default, sia le nuove ricette che il codice sorgente vengono inseriti in una directory "workspace" all'interno dell'eSDK. Il comando `devtool upgrade` aggiorna una ricetta esistente in modo da poterla compilare con un set aggiornato di file sorgente.

Si può leggere sul workflow di `devtool` nel Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (eSDK) nella sezione "*Using devtool in Your SDK Workflow*".

- *Extensible Software Development Kit (eSDK)*: L'eSDK fornisce una toolchain di cross-sviluppo e librerie specifiche per il contenuto di una determinata immagine. L'eSDK semplifica l'aggiunta di nuove applicazioni e librerie a un'immagine, la modifica del codice sorgente di un componente esistente, il test delle modifiche sull'hardware target e l'integrazione con il resto del sistema di build OpenEmbedded. L'eSDK offre un'esperienza di toolchain arricchita dal potente set di comandi `devtool` ottimizzati per l'ambiente Yocto Project.

Per informazioni sull'eSDK, consultare il manuale *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)*.

- *Toaster*: Toaster è un'interfaccia web per il sistema di build OpenEmbedded di Yocto Project. Toaster consente di configurare, eseguire e visualizzare informazioni sulle build. Per ulteriori informazioni su Toaster, consultare il manuale *Manuale Utente di Toaster*.
- *Estensione VSCode IDE*: L'estensione **Yocto Project BitBake** per Visual Studio Code offre una ricca serie di funzionalità per lavorare con le ricette BitBake. L'estensione fornisce evidenziazione della sintassi, suggerimenti al passaggio del mouse e completamento automatico per i file BitBake, nonché per i linguaggi Python e Bash embedded. Ulteriori visualizzazioni e comandi consentono di esplorare, compilare e modificare le ricette in modo efficiente. Offre anche l'integrazione con l'SDK per la cross-compilazione e il debug tramite `devtool`.

Scoprire di più sull'estensione VS Code sulla [pagina principale dell'estensione](#).

## Strumenti di Produzione

Ecco alcuni strumenti utili per le attività di produzione con Yocto Project:

- *Auto Upgrade Helper*: Questa utility, se utilizzata insieme all'*OpenEmbedded Build System* (BitBake e OE-Core), genera automaticamente gli aggiornamenti per le ricette basate su nuove versioni pubblicate a monte [upstream]. Per informazioni sulla configurazione, consultare *Using the Auto Upgrade Helper (AUH)*.
- *Recipe Reporting System*: Il sistema di segnalazione delle ricette tiene traccia delle versioni delle ricette disponibili per Yocto Project. Lo scopo principale del sistema è quello di aiutare a gestire le ricette mantenute e di offrire una panoramica dinamica del progetto. Il sistema di segnalazione delle ricette si basa su *OpenEmbedded Layer Index*, un sito web che indicizza i layer di OpenEmbedded-Core.
- *Patchwork*: **Patchwork** è un fork di un progetto originariamente avviato da **Oz Labs**. Il progetto è un sistema di tracciamento basato sul web, progettato per semplificare il processo di integrazione dei contributi in un progetto. Yocto Project utilizza Patchwork come strumento organizzativo per gestire le patch, che sono migliaia per ogni release.
- *AutoBuilder*: AutoBuilder è un progetto che automatizza i test di build e il controllo qualità (QA). Utilizzando AutoBuilder, disponibile pubblicamente, chiunque può verificare lo stato del branch di sviluppo corrente dei repository principali (*OpenEmbedded-Core (OE-Core)* e *BitBake*).

**Nota**

AutoBuilder si basa su [buildbot](#).

Uno degli obiettivi di Yocto Project è quello di essere leader nel settore open source con un progetto che automatizza le procedure di test e QA. In tal modo, il progetto incoraggia una comunità di sviluppatori che pubblica piani di QA e di test, li dimostra pubblicamente e promuove lo sviluppo di strumenti che automatizzano le procedure di test e QA a beneficio dell'intera comunità.

Per saperne di più sull'AutoBuilder utilizzato da Yocto Project, consultare la documentazione [qui](#).

- *Pseudo*: Pseudo è l'implementazione in Yocto Project di [fakeroot](#), utilizzato per eseguire comandi in un ambiente che apparentemente dispone di privilegi di root.

Durante una build, può essere necessario eseguire operazioni che richiedono privilegi di amministratore di sistema. Ad esempio, potrebbe essere necessario definire la proprietà o i permessi dei file. Pseudo è uno strumento utilizzabile direttamente o tramite la variabile d'ambiente `LD_PRELOAD`. Entrambi i metodi consentono di eseguire queste operazioni con successo anche senza privilegi di amministratore di sistema.

Grazie a Pseudo, Yocto Project non necessita mai di privilegi di root per creare immagini per il sistema target.

Si possono trovare maggiori informazioni su Pseudo nella sezione "[Fakeroot e Pseudo](#)".

## Componenti di Open-Embedded Build System

Ecco i componenti associati al *OpenEmbedded Build System*:

- *BitBake*: BitBake è un componente fondamentale di Yocto Project e viene utilizzato dal sistema di build OpenEmbedded per creare immagini. Sebbene BitBake sia essenziale per il sistema di build, viene gestito separatamente da Yocto Project.

BitBake è un motore generico per l'esecuzione di task che consente di eseguire in modo efficiente e parallelo task di shell e Python, gestendo al contempo complesse dipendenze tra i task. In breve, BitBake è un motore di build che funziona tramite ricette scritte in un formato specifico per eseguire insieme i task.

Per ulteriori informazioni su BitBake, consultare il [Manuale Utente di BitBake](#).

- *OpenEmbedded-Core*: *OpenEmbedded-Core (OE-Core)* è un layer comune di metadati (ovvero ricette, classi e file associati) utilizzato dai sistemi derivati da OpenEmbedded, incluso il Yocto Project. Sia Yocto Project che il Progetto OpenEmbedded mantengono OpenEmbedded-Core. È possibile trovare i metadati di OE-Core nei repository sorgente di OpenEmbedded [Source Repositories](#).

Storicamente, Yocto Project integrava i metadati di OE-Core in tutto il sistema di riferimento dei repository sorgente di Yocto Project (Poky). Dopo la versione 1.0 di Yocto Project, Yocto Project e OpenEmbedded hanno concordato di collaborare e condividere un set di metadati di base comune (OE-Core), che contiene gran parte delle funzionalità precedentemente presenti in Poky. Questa collaborazione ha permesso di raggiungere un obiettivo di lunga data di OpenEmbedded: avere un core più strettamente controllato e di qualità garantita. I risultati si integrano perfettamente anche con l'obiettivo di Yocto Project di ottenere un numero ridotto di strumenti completi, anziché un gran numero di strumenti diversi.

Oggigiorno, il repository *Poky* non viene più aggiornato, poiché *bitbake-setup* è diventato il metodo preferito per configurare i repository e compilare la distribuzione *Poky*.

## Pacchetti per Piattaforme Target

Ecco i componenti associati ai pacchetti per le piattaforme target:

- *Matchbox*: Matchbox è un ambiente di base open source per X Window System, in esecuzione su piattaforme embedded non desktop come palmari, set-top box, chioschi e qualsiasi altro dispositivo in cui lo spazio sullo schermo, i meccanismi di input o le risorse di sistema siano limitati.

Matchbox è composto da una serie di applicazioni intercambiabili e opzionali che è possibile adattare a una specifica piattaforma non desktop per migliorarne l'usabilità in ambienti con risorse limitate.

È possibile trovare il codice sorgente di Matchbox in Yocto Project [Source Repositories](#).

- *Opkg*: Open PacKaGe management (opkg) è un sistema di gestione dei pacchetti leggero basato sul sistema di gestione dei pacchetti itsy (ipkg). Opkg è scritto in C e il suo funzionamento è simile a quello di Advanced Package Tool (APT) e Debian Package (dpkg).

Opkg è pensato per l'utilizzo su dispositivi Linux embedded e viene impiegato a tale scopo nei progetti [OpenEmbedded](#) e [OpenWrt](#), nonché in Yocto Project.

### Nota

Per quanto possibile, opkg mantiene la compatibilità con le versioni precedenti di ipkg e si conforma a un sottoinsieme del manuale delle policy di Debian relative ai file di controllo.

È possibile trovare il codice sorgente di opkg nei repository di Yocto Project [Source Repositories](#).

## Componenti Archiviati

La Build Appliance è un'immagine di macchina virtuale che consente di creare e avviare un'immagine Linux embedded personalizzata con Yocto Project utilizzando un sistema di sviluppo non Linux.

Storicamente, la Build Appliance era il secondo di tre metodi per utilizzare il Yocto Project su un sistema non nativo Linux.

1. *Hob*: Hob, ora deprecato e non più disponibile dalla versione 2.1 di Yocto Project, forniva un'interfaccia grafica rudimentale per Yocto Project. Toaster ha completamente sostituito Hob.
2. *Build Appliance*: Dopo Hob, è diventata disponibile la Build Appliance. Non è mai stato raccomandato di utilizzare la Build Appliance come ambiente di sviluppo di produzione quotidiano con Yocto Project. La Build Appliance era utile per provare lo sviluppo nell'ambiente di Yocto Project.
3. *CROPS*: In passato era una soluzione disponibile per lo sviluppo tramite Yocto Project su un sistema non nativo per Linux (<https://github.com/crops/poky-container>).

### 4.1.4 Metodi di Sviluppo

L'ambiente di sviluppo di Yocto Project prevede in genere un *Build Host* e un hardware target. Il Build Host viene utilizzato per creare immagini e sviluppare applicazioni, mentre l'hardware target viene utilizzato per eseguire il software distribuito.

Questa sezione fornisce un'introduzione alle opzioni o ai metodi di sviluppo disponibili per la configurazione del Build Host. A seconda delle preferenze di flusso di lavoro e del tipo di sistema operativo in esecuzione sul Build Host, sono disponibili diverse opzioni.

**Nota**

Per ulteriori dettagli sull'ambiente di sviluppo di Yocto Project, consultare il capitolo "*L'Ambiente di Sviluppo di Yocto Project*".

- *Host Linux Nativo*: Di gran lunga l'opzione migliore per un Build Host. Un sistema con Linux come sistema operativo nativo consente di sviluppare software utilizzando direttamente il tool *BitBake*. È possibile eseguire tutti gli aspetti dello sviluppo da una normale shell in una distribuzione Linux supportata.

Per informazioni su come configurare un Build Host su un sistema che esegue Linux come sistema operativo nativo, consultare la sezione "*Setting Up a Native Linux Host*" nel Manuale di Sviluppo dei Task di Yocto Project.

- *OCI Containers*: In genere, si utilizza un *OCI container* (ad esempio, con *Docker* o *Podman*), per configurare un *Build Host* che non esegue Linux (ad esempio, Microsoft Windows o macOS).
- *Windows Subsystem For Linux (WSL 2)*: È possibile utilizzare il Windows Subsystem For Linux versione 2 per configurare un Build Host con Windows 10 o versioni successive, oppure Windows Server 2019 o versioni successive.

Il Windows Subsystem For Linux consente a Windows di eseguire un kernel Linux reale all'interno di una macchina virtuale (VM) leggera.

Per informazioni su come configurare un Build Host con WSL 2, consultare la sezione "*Setting Up to Use Windows Subsystem For Linux (WSL 2)*" nel Manuale di Sviluppo dei Task di Yocto Project.

- *Toaster*: Indipendentemente dal sistema operativo in esecuzione sul Build Host, è possibile utilizzare Toaster per sviluppare software con Yocto Project. Toaster è un'interfaccia web per il *OpenEmbedded Build System* di Yocto Project. L'interfaccia consente di configurare ed eseguire le build. Le informazioni relative alle build vengono raccolte e memorizzate in un database. È possibile utilizzare Toaster per configurare e avviare build su più server di build remoti.

Per informazioni su Toaster e sul suo utilizzo, consultare la documentazione *Manuale Utente di Toaster*.

- *Utilizzo dell'Estensione VSCode*: Si può usare l'estensione *Yocto Project BitBake* per Visual Studio Code per avviare le build BitBake tramite un'interfaccia grafica

Maggiori informazioni sull'estensione VS Code sulla [pagina del marketplace dell'estensione](#)

#### 4.1.5 Distribuzione Embedded di Riferimento (Poky)

"Poky", che si pronuncia *Pock-ee*, è il nome della distribuzione di riferimento o kit del sistema operativo di riferimento di Yocto Project. Questa distribuzione di riferimento è rappresentata da un file di configurazione *DISTRO* che si trova in *meta-poky*.


**⚠ Avvertimento**

Sebbene Poky sia una specifica di distribuzione "completa", testata e sottoposta a QA, non è possibile utilizzarla così com'è per un prodotto finale.

Poky ha un ciclo di rilascio regolare e ben consolidato di sei mesi, descritto in dettaglio nel documento *Rilasci di Yocto Project e Iter dei Rilasci Stabili* del Manuale di Riferimento di Yocto Project.

## 4.1.6 Workflow del Sistema di Build OpenEmbedded

*OpenEmbedded Build System* usa un "workflow" per la generazione di immagini e SDK. La figura seguente illustra tale flusso di lavoro:



Ecco un breve riepilogo del "workflow":

1. Gli sviluppatori specificano architettura, policy, patch e dettagli di configurazione.
2. Il sistema di build recupera e scarica il codice sorgente dalla posizione specificata. Il sistema di build supporta metodi standard come i tarball o i sistemi di repository di codice sorgente come Git.
3. Una volta scaricato il codice sorgente, il sistema di build estrae i file in un'area di lavoro locale dove vengono applicate le patch ed eseguiti i passaggi comuni per la configurazione e la compilazione del software.
4. Il sistema di build installa quindi il software in un'area di staging temporanea dove viene utilizzato il formato del pacchetto binario selezionato (DEB, RPM o IPK) per creare il pacchetto del software.
5. Diversi controlli di qualità e di integrità vengono eseguiti durante l'intero processo di build.
6. Dopo la creazione dei file binari, il sistema di build genera un feed di pacchetti binari che viene utilizzato per creare l'immagine finale del file system root.
7. Il sistema di build genera l'immagine del file system e un *SDK* (Software Development Kit) personalizzato per lo sviluppo parallelo delle applicazioni.

Per una descrizione dettagliata di questo flusso di lavoro, consultare la sezione *"Concetti del Sistema di Build OpenEmbedded"*.



### 4.1.7 Alcuni Termini di Base

Per imparare a usare Yocto Project, è utile conoscere alcuni termini fondamentali. Sebbene la sezione "*Yocto Project Terms*" del Manuale di Riferimento di Yocto Project contenga un elenco di termini, questa sezione fornisce le definizioni di alcuni termini utili per iniziare:

- *File di Configurazione*: File che contengono definizioni globali di variabili, variabili definite dall'utente e informazioni sulla configurazione hardware. Questi file indicano al *OpenEmbedded Build System* cosa compilare e cosa includere nell'immagine per supportare una specifica piattaforma.
- *Extensible Software Development Kit (eSDK)*: Un SDK personalizzato per gli sviluppatori di applicazioni. Questo eSDK consente agli sviluppatori di integrare le proprie librerie e modifiche di programmazione nell'immagine, rendendo il codice disponibile ad altri sviluppatori di applicazioni. Per informazioni sull'eSDK, consultare il manuale *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)*.
- *Layer*: Una raccolta di metadati correlati, che può includere ricette, file di configurazione della macchina, file di configurazione della distribuzione e/o file di classe. I layer consentono di consolidare i metadati correlati per personalizzare la build. I layer isolano inoltre le informazioni utilizzate durante la compilazione per architetture multiple. I layer sono gerarchici e possono sovrascrivere le specifiche precedenti. È possibile includere un numero qualsiasi di layer disponibili da Yocto Project e personalizzare la build aggiungendo i propri layer. È possibile cercare i layer utilizzati all'interno di Yocto Project nell'Indice dei layer.

Per informazioni più dettagliate sui layer, consultare la sezione "*Comprendere e Creare i Layer*" nel Manuale di Riferimento di Yocto Project. Per una discussione specifica sui layer BSP, consultare la sezione "*Layer BSP*" nella Guida degli Sviluppatori di Board Support Packages (BSP) di Yocto Project.

- *Metadata*: Un elemento chiave di Yocto Project sono i metadati, utilizzati per costruire una distribuzione Linux e contenuti nei file che il sistema di build OpenEmbedded analizza durante la creazione di un'immagine. In generale, i metadati includono ricette, file di configurazione e altre informazioni che si riferiscono alle istruzioni di build stesse, nonché i dati utilizzati per controllare cosa viene compilato e gli effetti della build. I metadati includono anche comandi e dati utilizzati per indicare quali versioni del software vengono utilizzate, da dove vengono ottenute e modifiche o aggiunte al software stesso (patch o file ausiliari) utilizzate per correggere bug o personalizzare il software per l'uso in una situazione particolare. OpenEmbedded-Core è un importante insieme di metadati validati.
- *Sistema di Build OpenEmbedded*: I termini "BitBake" e "sistema di build" vengono talvolta utilizzati per indicare l'OpenEmbedded Build System.

BitBake è un gestore di task e un motore di esecuzione che analizza le istruzioni (ovvero le ricette) e i dati di configurazione. Dopo una fase di analisi, BitBake crea un albero delle dipendenze per ordinare la compilazione, pianifica la compilazione del codice incluso e infine esegue la creazione dell'immagine Linux personalizzata specificata (distribuzione). BitBake è simile al tool `make`.

Durante un processo di compilazione, il sistema di build tiene traccia delle dipendenze ed esegue una compilazione nativa o incrociata [cross] di ciascun pacchetto. Come primo passo in una configurazione di cross-compilazione, il framework tenta di creare una toolchain di cross-compilazione (ovvero un SDK estensibile) adatta alla piattaforma target.

- *OpenEmbedded-Core (OE-Core)*: OE-Core è un insieme di metadati composto da ricette di base, classi e file associati, pensati per essere comuni a molti sistemi derivati da OpenEmbedded, incluso Yocto Project. OE-



Core è un sottoinsieme curato di un repository originale sviluppato dalla comunità OpenEmbedded, ridotto a un insieme più piccolo e centrale di ricette continuamente validate. Il risultato è un insieme di ricette di base rigorosamente controllato e di qualità garantita.

È possibile visualizzare i metadati nella directory `meta` del [Source Repositories](#) di Yocto Project.

- *Pacchetti*: Nel contesto di Yocto Project, questo termine si riferisce all'output impacchettato di una ricetta prodotto da BitBake (ovvero una "baked recipe"). Un pacchetto è generalmente costituito dai binari compilati prodotti dai sorgenti della ricetta. Si "impacchetta" qualcosa eseguendola tramite BitBake.

Vale la pena notare che il termine "pacchetto" può, in generale, avere significati sfumati. Ad esempio, i pacchetti a cui si fa riferimento nella sezione "*Pacchetti Richiesti per l'Host di Build*" del Manuale di Riferimento di Yocto Project sono binari compilati che, una volta installati, aggiungono funzionalità alla distribuzione Linux host.

Un altro punto degno di nota è che storicamente, all'interno di Yocto Project, le ricette venivano chiamate pacchetti [package]; da qui l'esistenza di diverse variabili BitBake apparentemente denominate in modo errato (ad esempio, *PR*, *PV* e *PE*).

- *Poky*: Poky è una distribuzione embedded di riferimento e una configurazione di test di riferimento. Poky fornisce quanto segue:
  - Una distribuzione funzionale di base (*DISTRO*) utilizzata per illustrare come personalizzare una distribuzione.
  - Un mezzo per testare i componenti di Yocto Project (ovvero, Poky viene utilizzato per validare Yocto Project).

Poky non è una distribuzione a livello di prodotto. Piuttosto, è un buon punto di partenza per la personalizzazione.

- *Ricetta*: La forma più comune di metadati. Una ricetta contiene un elenco di impostazioni e task (ovvero istruzioni) per la creazione di pacchetti che vengono poi utilizzati per costruire l'immagine binaria. Una ricetta descrive da dove reperire il codice sorgente e quali patch applicare. Le ricette descrivono le dipendenze per le librerie o per altre ricette, nonché le opzioni di configurazione e compilazione. Le ricette correlate sono consolidate in un layer.

## 4.2 L'Ambiente di Sviluppo di Yocto Project

Questo capitolo esamina l'ambiente [environment] di sviluppo di Yocto Project. Il capitolo fornisce concetti relativi all'ambiente di sviluppo di Yocto Project che aiutano a comprendere come si lavora in un ambiente open source, che è molto diverso rispetto al lavoro svolto in un ambiente proprietario chiuso.

Nello specifico, questo capitolo tratta la filosofia open source, i repository del codice sorgente, i flussi di lavoro, Git e le licenze.

### 4.2.1 Filosofia Open Source

La filosofia open source è caratterizzata da uno sviluppo software guidato dalla produzione e dalla collaborazione tra pari attraverso una comunità attiva di sviluppatori. Questo si contrappone ai modelli di sviluppo centralizzati più standard utilizzati dalle aziende di software commerciali, dove un insieme finito di sviluppatori produce un prodotto

da vendere utilizzando una serie definita di procedure che in definitiva portano a un prodotto finale la cui architettura e il cui codice sorgente sono chiusi al pubblico.

I progetti open source hanno concettualmente diverse agende, approcci e processi di produzione concorrenti. Questi aspetti del processo di sviluppo possono provenire da chiunque nel pubblico (community) che abbia un interesse nel progetto software. L'ambiente open source presenta nuove problematiche relative a copyright, licenze, dominio e consumatori, che lo distinguono dagli ambienti di sviluppo più tradizionali. In un ambiente open source, il prodotto finale, il codice sorgente e la documentazione sono tutti disponibili al pubblico gratuitamente.

Un esempio emblematico di progetto open source è il kernel Linux, inizialmente concepito e creato dallo studente finlandese di informatica Linus Torvalds nel 1991. Al contrario, un buon esempio di progetto non open source è la famiglia di sistemi operativi Windows sviluppata da Microsoft Corporation.

Wikipedia offre un'ottima [descrizione storica della Open Source Philosophy](#). È inoltre possibile trovare informazioni utili su come partecipare alla Linux Community [qui](#).

### 4.2.2 Host di Sviluppo

Un host di sviluppo, o *Build Host* è fondamentale per utilizzare Yocto Project. Poiché l'obiettivo di Yocto Project è sviluppare immagini o applicazioni che vengano eseguite su hardware embedded, lo sviluppo di tali immagini e applicazioni avviene generalmente su un sistema non destinato all'esecuzione del software, ovvero l'host di sviluppo.

È necessario configurare un host di sviluppo per poterlo utilizzare con Yocto Project. Molti ritengono che sia preferibile utilizzare una macchina Linux nativa come host di sviluppo. Tuttavia, è possibile utilizzare un sistema che non esegue Linux come sistema operativo come host di sviluppo. Se si dispone di un sistema basato su Mac o Windows, è possibile configurarlo come host di sviluppo utilizzando un [container OCI](#) (tramite [Docker](#) o [Podman](#)). Una volta completata la configurazione del container, si avrà accesso a un ambiente shell simile a quello di un host di sviluppo basato su Linux.

Se l'host di sviluppo è un sistema che esegue una distribuzione Linux, è comunque necessario prepararlo per l'utilizzo con Yocto Project. Bisogna assicurarsi che la distribuzione Linux installata sul sistema supporti Yocto Project e che siano installati i pacchetti host necessari per lo sviluppo con Yocto Project. Per i passaggi necessari alla configurazione di un host di sviluppo Linux, consultare la sezione "[Setting Up a Native Linux Host](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

Una volta configurato il sistema host di sviluppo per utilizzare Yocto Project, esistono diversi modi per lavorare nell'ambiente di Yocto Project:

- *Riga di Comando, BitBake e Shell*: Lo sviluppo tradizionale in Yocto Project prevede l'utilizzo del sistema di compilazione [build] [OpenEmbedded Build System](#), che si basa su BitBake, in un ambiente a riga di comando da una shell sul sistema host di sviluppo. È possibile farlo da un sistema host nativo Linux o da un container. In entrambi i casi, si creano, modificano e compilano immagini e applicazioni all'interno di un ambiente basato su shell, utilizzando componenti e strumenti disponibili tramite la distribuzione Linux e Yocto Project.

Per una descrizione generale delle procedure di compilazione, consultare la sezione "[Building a Simple Image](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

- *Sviluppo di Board Support Package (BSP)*: Lo sviluppo di BSP prevede l'utilizzo di Yocto Project per creare e testare layer che consentono un facile sviluppo di immagini e applicazioni destinate a hardware specifici. Per sviluppare BSP, è necessario eseguire alcuni passaggi aggiuntivi rispetto a quelli descritti nella configurazione di un host di sviluppo.

Il *Manuale del Board Support Package (BSP) di Yocto Project* fornisce informazioni sullo sviluppo dei BSP. Per dettagli sulla preparazione dell'host di sviluppo, consultare la sezione "*Preparazione dell'Host di Build per Lavorare con i Layer BSP*" nella Guida dello Sviluppatore del Board Support Package (BSP) di Yocto Project.

- *Sviluppo del Kernel:* Se si intende sviluppare kernel utilizzando Yocto Project, è probabile che si utilizzi `devtool`. Un flusso di lavoro che utilizza `devtool` velocizza lo sviluppo del kernel riducendo i tempi del ciclo di iterazione.

Il *Manuale di Sviluppo del Kernel Linux di Yocto Project* fornisce informazioni sullo sviluppo del kernel. Per dettagli sulla preparazione dell'host di sviluppo, consultare la sezione "*Preparazione dell'Host di Build per Lavorare sul Kernel*." nel Manuale di Sviluppo del Kernel Linux di Yocto Project.

- *Utilizzo di Toaster:* L'altro metodo di sviluppo di Yocto Project che prevede l'utilizzo di un'interfaccia che di fatto mette Yocto Project in background è Toaster. Toaster fornisce un'interfaccia per il sistema di build OpenEmbedded. L'interfaccia consente di configurare ed eseguire le compilazioni. Le informazioni sulle compilazioni vengono raccolte e memorizzate in un database. È possibile utilizzare Toaster per configurare e avviare compilazioni su più server di compilazione remoti.

Per le istruzioni su come configurare l'host di sviluppo per utilizzare Toaster e su come utilizzare Toaster in generale, consultare il *Manuale Utente di Toaster*.

- *Utilizzo dell'Estensione VSCode:* Si può usare l'estensione **Yocto Project BitBake** per Visual Studio Code per avviare le build BitBake tramite un'interfaccia grafica

Maggiori informazioni sull'estensione VS Code nella [pagina del marketplace dell'estensione](#).

### 4.2.3 I Repository del Codice Sorgente di Yocto Project

Il team di Yocto Project mantiene repository di codice sorgente completi per tutti i file di Yocto Project all'indirizzo <https://git.yoctoproject.org/>. Questo browser di codice sorgente basato sul web è organizzato in categorie per funzione, come plugin IDE, Matchbox, Poky, kernel Linux Yocto e così via. Dall'interfaccia, è possibile cliccare su qualsiasi elemento nella colonna "Name" e visualizzare l'URL in fondo alla pagina necessario per clonare un repository Git per quell'elemento specifico. Avere una copia locale di questi repository Git consente di apportare modifiche, contribuire alla cronologia e, in definitiva, migliorare gli strumenti di Yocto Project, i pacchetti di supporto per le schede (BSP) e altro ancora.


Per qualsiasi versione supportata di Yocto Project, è anche possibile visitare il sito web di Yocto Project all'indirizzo [Sito Web di Yocto Project](#) e selezionare la voce "Releases" dal menù "Development" per scaricare un tarball dei repository, un tarball BSP supportato o gli strumenti di Yocto Project. L'estrazione di questi archivi tar fornisce un'istantanea dei file rilasciati.

#### Nota

- Il metodo consigliato per configurare Yocto Project è utilizzare *Git* per creare una copia locale dei repository upstream.
- Si deve lavorare sempre su branch corrispondenti sia per il repository BSP selezionato, sia per i repository *OpenEmbedded-Core (OE-Core)* e *BitBake*. Ad esempio, se è stato effettuato il checkout del branch "black-sail" di *OpenEmbedded-Core (OE-Core)* e si intende usare `meta-intel`, si deve effettuare il checkout del branch "blacksail" di `meta-intel`.

In sintesi, ecco dove è possibile trovare i file di progetto necessari per lo sviluppo:


- **Source Repositories:** Quest'area contiene *BitBake*, *OpenEmbedded-Core (OE-Core)*, documentazione Yocto e altri layer di metadati. È possibile creare copie locali dei repository Git per ciascuna di queste aree.



The screenshot shows the 'Source Repositories' page of the Yocto Project. It features a search bar and a table listing various repositories. The table has three columns: Name, Description, and Idle. The repositories are categorized into groups like Poky, Poky Support, Yocto Automated Testing, Yocto Metadata Layers - Platinum Members, Yocto Metadata Layers - Autobuilder Tested, and Yocto Metadata Layers - Member Layers.

| Name                                        | Description                                                                         | Idle     |
|---------------------------------------------|-------------------------------------------------------------------------------------|----------|
| -Poky                                       |                                                                                     |          |
| poky                                        | Poky Build Tool and Metadata                                                        | 4 days   |
| poky-contrib                                | Poky Built Tool and Metadata - User Contributions Tree                              | 8 hours  |
| yocto-docs                                  | Versioned project documentation                                                     | 21 min.  |
| -Poky Support                               |                                                                                     |          |
| poky-config                                 | Combo-layer configuration and support scripts for the poky repository               | 4 days   |
| poky-contrib-archive                        | User contributions older than January 1st 2013                                      | 2 years  |
| -Yocto Automated Testing                    |                                                                                     |          |
| poky-buildhistory                           | Autobuilder Saved Build History (for Poky master)                                   | 11 hours |
| yocto-buildstats                            | Build performance test results from the Yocto project                               | 1 min.   |
| yocto-testresults                           | Test results published from the public autobuilder                                  | 9 hours  |
| yocto-testresults-contrib                   | Test results published from contributor autobuilders and QA teams                   | 8 hours  |
| -Yocto Metadata Layers - Platinum Members   |                                                                                     |          |
| meta-arm                                    | Layer containing support for Arm products                                           | 4 days   |
| meta-aws                                    | Layer containing Amazon Web Services (AWS) device software support metadata         | 43 min.  |
| meta-intel                                  | Layer containing Intel hardware support metadata                                    | 35 hours |
| meta-ti                                     | Layer containing TI hardware support metadata                                       | 4 hours  |
| meta-xilinx                                 | Layer containing Xilinx hardware support metadata                                   | 8 months |
| -Yocto Metadata Layers - Autobuilder Tested |                                                                                     |          |
| meta-gplv2                                  | GPLv2 versions of software where upstream has moved to GPLv3 licenses               | 4 weeks  |
| meta-mingw                                  | Layer for mingw based SDKs                                                          | 4 weeks  |
| meta-yocto                                  | Yocto Project integration layers (Poky distro configuration, reference hardware ... | 19 hours |
| -Yocto Metadata Layers - Member Layers      |                                                                                     |          |
| meta-amd                                    | Layer containing AMD hardware support metadata                                      | 3 months |
| meta-freescale                              | Layer containing NXP hardware support metadata                                      | 43 min.  |
| meta-renesas                                | Layer supporting Renesas Electronics SoCs                                           | 2 years  |

- **Pagina delle Release:** Il sito web di Yocto Project include una pagina "Releases" accessibile tramite il menù "Development" che consente di scaricare qualsiasi release, tool e Board Support Package (BSP) di Yocto Project in formato tarball. I link ipertestuali puntano ai file tarball nella directory <https://downloads.yoctoproject.org/releases/yocto/>.



The screenshot shows the 'Software : Downloads' page of the Yocto Project. It features a navigation bar with links to SOFTWARE, DOCS, COMMUNITY, LEARN, ECOSYSTEM, ABOUT, and JOIN. The main content area is titled 'RELEASE YP CORE - LANGDALE 4.1.3 - 2023.03.15' and includes a 'RELEASE ARCHIVE' link. The page provides instructions on how to clone the repository using Git or download the tarball. It also includes a section for 'TOOLS' with links to 'BUILD APPLIANCE - LANGDALE 4.1.3' and 'BUILDTOOLS ESDK - LANGDALE 4.1.3'. A 'Privacy - Terms' link is visible in the bottom right corner.

**SOFTWARE : DOWNLOADS**

**RELEASE YP CORE - LANGDALE 4.1.3 - 2023.03.15** [RELEASE ARCHIVE](#)

The Yocto Project® build system (BitBake and the OE-Core metadata) is packaged with the reference distro (called Poky). This allows you to try out the whole system. You can create a binary image of Poky as is, or alter the Poky recipes and layers for use in your customized work.

Git is preferred to a tarball download. If you use the former, then code updates can easily be applied to your code base. Using the latter requires you to update your code base yourself, and the documents are slightly older.

The tools and bsp's below are not included. You must download each separately, and they are specific to the version of software you are using.

[git clone -b langdale git://git.yoctoproject.org/yocto](#)

or download

[DOWNLOAD YP CORE - LANGDALE 4.1.3](#)

[RELEASE INFORMATION - YP CORE - LANGDALE 4.1.3](#)

**TOOLS**

**BUILD APPLIANCE - LANGDALE 4.1.3**  
The Build Appliance is a virtual machine which enables you to build and boot a custom embedded Linux image with the Yocto Project using a non-Linux de... [READ MORE](#)

**BUILDTOOLS ESDK - LANGDALE 4.1.3**  
This buildtools SDK contains the needed versions of various programs to build Yocto Project on most distributions.FeaturesPython3 3.10.6git 2.37.3tar ... [READ MORE](#)

[Privacy - Terms](#)

## 4.2.4 Flussi di Lavoro Git e Yocto Project

Lo sviluppo con Yocto Project richiede probabilmente l'uso di [Git](#). Git è un sistema di controllo di versione distribuito, gratuito e open source, utilizzato in molti ambienti di sviluppo collaborativo. Questa sezione illustra i concetti relativi ai flussi di lavoro con Yocto Project e Git. In particolare, vengono descritte le pratiche di base che illustrano ruoli e azioni in un ambiente di sviluppo collaborativo.

### Nota

Se si ha già familiarità con questo tipo di ambiente di sviluppo, si può saltare questa sezione.

I file di Yocto Project vengono gestiti tramite Git in "branches", le cui cronologie Git tengono traccia di ogni modifica e la cui struttura fornisce branch per tutte le funzionalità divergenti. Sebbene non sia obbligatorio utilizzare Git, molti progetti open source lo fanno.

In Yocto Project, una figura chiave, chiamata "maintainer", è responsabile dell'integrità del branch di sviluppo di un determinato repository Git. Il branch di sviluppo è il repository "upstream" da cui vengono generate le build finali o più recenti di un progetto. Il responsabile della manutenzione ha il compito di accettare le modifiche da altri sviluppatori e di organizzare la struttura dei branch sottostante in modo che rifletta le strategie di rilascio e così via.

### Nota

Per informazioni su come individuare chi è responsabile (mantiene) una particolare area di codice in Yocto Project, consultare la sezione "[Identificazione del Componente](#)" della Guida per i Collaboratori di Yocto Project e di OpenEmbedded.


I repository Git di Yocto Project possono anche avere repository Git di contributi upstream con suffisso `-contrib`. È possibile visualizzare tutti i branch di questi repository tramite l'interfaccia web di [Source Repositories](#). Questi branch contengono le modifiche (commit) al progetto state inviate o confermate dal team di sviluppo di Yocto Project e dai membri della community che contribuiscono al progetto. Il manutentore determina se le modifiche sono idonee per essere spostate dai branch "contrib" al branch "master" del repository Git.

Gli sviluppatori (inclusi i membri della community che contribuiscono) creano e mantengono repository clonati dei branch upstream. I repository clonati sono locali alle rispettive piattaforme di sviluppo e vengono utilizzati per implementare le modifiche. Quando uno sviluppatore è soddisfatto di una particolare funzionalità o modifica, ne effettua il "push" al repository "contrib" appropriato.

Gli sviluppatori sono responsabili di mantenere aggiornato il proprio repository locale con il branch upstream su cui stanno lavorando. Sono inoltre responsabili della risoluzione di eventuali conflitti che potrebbero sorgere all'interno di file su cui lavorano simultaneamente più persone. Tutto questo lavoro viene svolto localmente sull'host di sviluppo prima che qualsiasi modifica venga inviata all'area "contrib" e analizzata dal manutentore.

Esiste un metodo piuttosto formale con cui gli sviluppatori effettuano il commit delle modifiche e le inviano [push] all'area "contrib", per poi richiedere al manutentore di includerle in un branch upstream. Questo processo è chiamato "submitting a patch" [invio di una patch] o "submitting a change" [invio di una modifica]. Per informazioni sull'invio di patch e modifiche, consultare la sezione "[Apportare Modifiche a un Componente](#)" nella Guida per i Collaboratori di Yocto Project e di OpenEmbedded.

In sintesi, esiste un unico punto di accesso per le modifiche al branch di sviluppo del repository Git, controllato dal manutentore del progetto. Un gruppo di sviluppatori sviluppa, testa e invia autonomamente le modifiche alle aree "contrib" affinché il manutentore le esamini. Il manutentore sceglie quindi quali modifiche verranno integrate in modo permanente nel progetto.



Sebbene ogni ambiente di sviluppo sia unico, esistono alcune best practice o metodi che contribuiscono a un flusso di lavoro più fluido. L'elenco seguente descrive alcune di queste pratiche. Per ulteriori informazioni sui flussi di lavoro di Git, consultare gli argomenti relativi ai flussi di lavoro nel [Libro su Git della Community](#).

- *Apportare Piccole Modifiche:* È preferibile che le modifiche da sottoporre a commit siano di piccole dimensioni, piuttosto che raggruppare molte modifiche eterogenee in un unico commit. Questa pratica non solo semplifica la gestione, ma consente anche al manutentore di includere o rifiutare le modifiche con maggiore facilità.
- *Apportare Modifiche Complete:* È inoltre buona norma lasciare il repository in uno stato che consenta di compilare correttamente il progetto. In altre parole, non effettuate il commit di metà di una funzionalità per poi aggiungere l'altra metà con un commit separato in un secondo momento. Ogni commit dovrebbe portare da uno stato di progetto compilabile a un altro stato compilabile.
- *Utilizzare i Branch Liberamente:* È molto semplice creare, utilizzare ed eliminare branch locali nel proprio repository Git di lavoro sull'host di sviluppo. Si può assegnare a questi branch qualsiasi nome. È utile assegnare loro nomi associati alla specifica funzionalità o modifica su cui si sta lavorando. Una volta terminata una funzionalità o una modifica e dopo averla unita al branch di sviluppo locale, è sufficiente eliminare il branch temporaneo.
- *Merge delle Modifiche:* Il comando `git merge` consente di unire le modifiche da un branch a un altro. Questo processo è particolarmente utile quando più sviluppatori lavorano su parti diverse della stessa funzionalità. L'unione [merging] delle modifiche identifica automaticamente anche eventuali collisioni o "conflitti" che potrebbero verificarsi a seguito della modifica delle stesse righe di codice da parte di due sviluppatori diversi.
- *Gestione dei Branch:* Poiché i branch sono facili da usare, è consigliabile utilizzare un sistema in cui i branch indichino diversi livelli di prontezza del codice. Ad esempio, è possibile avere un branch "work" per lo sviluppo, un branch "test" in cui il codice o la modifica vengono testati, un branch "stage" in cui le modifiche sono pronte per essere confermate e così via. Man mano che il progetto si sviluppa, è possibile unire il codice tra i branch per riflettere stati di sviluppo sempre più stabili.

- *Utilizzo di Push e Pull:* Il flusso di lavoro push-pull si basa sul concetto di sviluppatori che "spingono" [pushing] commit locali a un repository remoto, che di solito è un repository di contributi. Questo flusso di lavoro si basa anche sul "tirare" [pulling] da parte degli sviluppatori degli stati noti del progetto nei propri repository di sviluppo locali. Il flusso di lavoro consente di scaricare facilmente le modifiche inviate da altri sviluppatori dal repository upstream alla propria area di lavoro, garantendo di avere sempre a disposizione il software più recente su cui sviluppare. Yocto Project include due script denominati `create-pull-request` e `send-pull-request`, forniti con la release per facilitare questo flusso di lavoro. Questi script si trovano nella cartella `scripts` di *OpenEmbedded-Core (OE-Core)*. Per informazioni su come utilizzare questi script, consultare la sezione "*Uso di Script per il Push di una Modifica Upstream e il Pull Request*" nella Guida per i Collaboratori di Yocto Project e di OpenEmbedded.
- *Flusso di Lavoro per le Patch:* Questo flusso di lavoro consente di notificare al manutentore, tramite e-mail, che si ha una modifica (o patch) da prendere in considerazione per il branch di sviluppo del repository Git. Per inviare questo tipo di modifica, formattare la patch e inviare l'e-mail utilizzando i comandi Git `git format-patch` e `git send-email`. Per informazioni su come utilizzare questi script, consultare la sezione "*Apportare Modifiche a un Componente*" nella Guida per i Collaboratori di Yocto Project e di OpenEmbedded.

## 4.2.5 Git

Yocto Project fa ampio uso di Git, un sistema di controllo di versione distribuito, gratuito e open source. Git supporta lo sviluppo distribuito, lo sviluppo non lineare e può gestire progetti di grandi dimensioni. È consigliabile avere una conoscenza di base di come Git gestisce i progetti e di come utilizzarlo se si intende utilizzare Yocto Project per lo sviluppo. Questa sezione fornisce una rapida panoramica del funzionamento di Git e un riepilogo di alcuni comandi Git essenziali.

### Nota

- Per ulteriori informazioni su Git, consultare <https://git-scm.com/docs>.
- Se è necessario scaricare Git, si consiglia di aggiungerlo al sistema tramite i "software store" della propria distribuzione (ad esempio, per Ubuntu, utilizzare la funzionalità Ubuntu Software). Per la pagina di download di Git, consultare <https://git-scm.com/download>.

## Repository, Tag e Branch

Come accennato brevemente nella sezione precedente e anche nella sezione "*Flussi di Lavoro Git e Yocto Project*", Yocto Project gestisce i repository del codice sorgente all'indirizzo <https://git.yoctoproject.org/>. Se si osserva questa interfaccia web dei repository, ogni elemento corrisponde a un repository Git separato.

I repository Git utilizzano tecniche di branching che tengono traccia delle modifiche al contenuto (non ai file) all'interno di un progetto (ad esempio, una nuova funzionalità o la documentazione aggiornata). La creazione di una struttura ad albero basata sulla divergenza del progetto consente di ottenere un'eccellente cronologia delle modifiche durante l'intero ciclo di vita del progetto. Questa metodologia permette inoltre di disporre di un ambiente in cui è possibile effettuare numerose sperimentazioni locali sui progetti durante lo sviluppo di modifiche o nuove funzionalità.

Un repository Git rappresenta tutte le attività di sviluppo relative a un determinato progetto. Ad esempio, il repository Git `yocto-docs` contiene tutte le modifiche e gli sviluppi relativi a quel repository nel corso della sua intera esistenza.



Ciò significa che tutte le modifiche che compongono tutte le release vengono registrate. Il repository mantiene una cronologia completa delle modifiche.

È possibile creare una copia locale di qualsiasi repository "clonandolo" con il comando `git clone`. Quando si clona un repository Git, si ottiene una copia identica del repository sul proprio sistema di sviluppo. Una volta ottenuta una copia locale di un repository, è possibile procedere con lo sviluppo in locale.

È importante capire che Git tiene traccia delle modifiche al contenuto e non ai file. Git utilizza i "branch" per organizzare i diversi progetti di sviluppo. Ad esempio, il repository `yocto-docs` ha diversi branch, tra cui il branch corrente "blacksail", il branch "master" e molti branch per le release precedenti di Yocto Project. È possibile visualizzare tutti i branch accedendo a `yocto-docs` e cliccando sul link [...] sotto l'intestazione "Branch".

Ciascuno di questi branch rappresenta un'area di sviluppo specifica. Il branch "master" rappresenta lo sviluppo corrente o più recente. Tutti gli altri branch rappresentano derivazioni del branch "master".

Quando si crea una copia locale di un repository Git, la copia ha lo stesso set di branch dell'originale. Ciò significa che è possibile utilizzare Git per creare un'area di lavoro locale (chiamata anche branch) che tenga traccia di uno specifico branch di sviluppo del repository Git di origine. In altre parole, è possibile configurare il proprio ambiente Git locale per lavorare su qualsiasi branch di sviluppo presente nel repository. Per illustrare meglio il concetto, si considerino i seguenti comandi Git di esempio:

```
$ cd ~
$ git clone https://git.yoctoproject.org/yocto-docs -b blacksail
```

Nell'esempio precedente, dopo essersi spostati nella directory home, il comando `git clone` crea una copia locale del repository Git `yocto-docs` e esegue il "checkout" di un branch locale chiamato "blacksail", che traccia il branch "origin/blacksail" del repository principale. Le modifiche apportate in questo branch influenzeranno in definitiva il branch "blacksail" del repository principale `yocto-docs`.

È importante capire che quando si crea e si seleziona un branch di lavoro locale in base al nome di un branch, l'ambiente locale corrisponde alla "tip" di quel particolare branch di sviluppo al momento della creazione del branch locale, che potrebbe essere diversa dai file presenti nel branch "master" del repository principale. In altre parole, creare e selezionare un branch locale in base al nome del branch "blacksail" non è la stessa cosa che selezionare il branch "master" nel repository. Continuare a leggere per scoprire come creare uno snapshot locale di una Release di Yocto Project.

Git usa i "tag" per contrassegnare modifiche specifiche nella struttura dei branch di un repository. In genere, un tag viene utilizzato per contrassegnare un punto specifico, come l'ultima modifica (o commit) prima del rilascio di un progetto. È possibile visualizzare i tag utilizzati nel repository Git `yocto-docs` accedendo a <https://git.yoctoproject.org/yocto-docs/> e cliccando sul link [...] sotto l'intestazione "Tag".

Alcuni tag chiave per il repository `yocto-docs` sono `kirkstone-4.0.30`, `scarthgap-5.0.1` e `blacksail-6.1`. Questi tag rappresentano le release di Yocto Project.

Quando si crea una copia locale del repository Git, si ha accesso anche a tutti i tag presenti nel repository upstream. Analogamente ai branch, è possibile creare e clonare un branch Git di lavoro locale basato sul nome di un tag. In questo modo, si ottiene un'istantanea del repository Git che riflette lo stato dei file al momento della modifica associata a quel tag. L'utilizzo più comune è quello di effettuare il checkout di un branch di lavoro corrispondente a una specifica release di Yocto Project. Ecco un esempio:



```
$ cd ~
$ git clone https://git.yoctoproject.org/yocto-docs
$ cd yocto-docs
$ git fetch --tags
$ git checkout tags/blacksail-6.1 -b my_blacksail-6.1
```

In questo esempio, il nome della directory principale del repository locale di Yocto Project è `yocto-docs`. Dopo essersi spostati nella directory `yocto-docs`, il comando `git fetch` rende disponibili localmente nel repository tutti i tag upstream. Infine, il comando `git checkout` crea e effettua il checkout di un branch chiamato "my\_blacksail-6.1" basato sul branch upstream il cui "HEAD" corrisponde al commit nel repository associato al tag "blacksail-6.1". I file nel repository ora corrispondono esattamente a quella specifica release di Yocto Project, così come è taggata nel repository Git upstream. È importante capire che quando si crea e si effettua il checkout di un branch di lavoro locale basato su un tag, l'ambiente corrisponde a un punto specifico nel tempo e non all'intero branch di sviluppo (ovvero, dalla "tip" [punta] del branch a ritroso).

## Comandi Base

Git offre un'ampia gamma di comandi che consentono di gestire le modifiche e collaborare durante l'intero ciclo di vita di un progetto. Fortunatamente, è possibile gestirlo anche con un set ridotto di operazioni e flussi di lavoro di base, una volta compresa la filosofia di Git. Non è necessario essere esperti di Git per utilizzarlo. Un buon punto di partenza per imparare i comandi Git di base è [questo](#).

Il seguente elenco di comandi Git descrive brevemente alcune operazioni di base per iniziare. Come per qualsiasi elenco di comandi, questo (nella maggior parte dei casi) mostra solo il comando base, omettendo i numerosi argomenti supportati. Consultare la documentazione di Git per descrizioni complete e strategie su come utilizzare questi comandi:

- *git init*: Inizializza un repository Git vuoto. Non è possibile utilizzare i comandi Git se non si dispone di un repository `.git`.
- *git clone*: Crea una copia locale di un repository Git, che si trova sullo stesso piano del repository Git di un altro sviluppatore o del repository upstream.
- *git add*: Aggiunge localmente all'indice utilizzato da Git per tenere traccia delle modifiche il contenuto aggiornato dei file. È necessario aggiungere all'area di staging tutti i file modificati prima di poterli confermare [commit].
- *git commit*: Crea un "commit" locale che documenta le modifiche apportate. Solo le modifiche aggiunte all'area di staging possono essere confermate. I commit vengono utilizzati a scopo storico, per verificare se il manutentore di un progetto accetta la modifica e, infine, per inviare la modifica dal repository Git locale al repository upstream del progetto.
- *git status*: Segnala eventuali file modificati che potrebbero dover essere aggiunti all'area di staging e fornisce un aggiornamento sullo stato dei commit locali rispetto al repository upstream.
- *git checkout branch-name*: Cambia il branch di lavoro locale e, in questa forma, presuppone che il branch locale esista già. Questo comando è analogo a "cd".
- *git checkout -b working-branch upstream-branch*: Crea e esegue il checkout di un nuovo branch di lavoro sulla macchina locale. Il branch locale traccia il branch upstream. Si può usare il proprio branch locale

per isolare il proprio lavoro. È consigliabile utilizzare branch locali quando si aggiungono funzionalità specifiche o si apportano modifiche. L'utilizzo di branch isolati facilita la rimozione delle modifiche qualora non funzionassero.

- *git branch*: Visualizza i branch locali esistenti associati al proprio repository locale. Il branch attualmente selezionato è indicato con un asterisco.
- *git branch -D branch-name*: Elimina un branch locale esistente. Ci si deve trovare in un branch locale diverso da quello che si sta eliminando per poter eliminare branch-name.
- *git pull --rebase*: Recupera le informazioni da un repository Git upstream e le inserisce nel proprio repository Git locale. Questo comando viene utilizzato per garantire la sincronizzazione con il repository da cui si prendono le modifiche (ad esempio, il branch "blacksail"). L'opzione `--rebase` garantisce che tutti i commit locali presenti nel proprio branch vengano mantenuti all'inizio del branch locale.
- *git push repo-name local-branch:upstream-branch*: Invia tutte le modifiche locali sottoposte a commit al repository Git upstream che il repository locale sta monitorando (ad esempio, un repository di contributi). Il manutentore del progetto preleva da questi repository per unire le modifiche (commit) nel branch appropriato del repository upstream del progetto.
- *git merge*: Unisce o aggiunge le modifiche da un branch locale del proprio repository con un altro branch. Quando si crea un repository Git locale, il branch predefinito potrebbe chiamarsi "main". Un flusso di lavoro tipico prevede la creazione di un branch temporaneo basato su "main" da utilizzare per lavorare in isolamento. Si apporteranno le modifiche in questo branch isolato, si aggiungeranno all'area di staging e si sottoporranno a commit localmente, si passerà al branch "main" e quindi si userà il comando `git merge` per applicare le modifiche dal branch isolato al branch attualmente selezionato (ad esempio, "main"). Una volta completata la fusione e si è finito di lavorare su quel branch isolato, lo si può eliminare in tutta sicurezza.
- *git cherry-pick commits*: Seleziona e applica commit specifici da un branch a un altro. A volte potrebbe non essere possibile unire tutte le modifiche di un branch con un altro, ma è necessario selezionarne alcune.
- *gitk*: Fornisce una visualizzazione grafica dei branch e delle modifiche nel repository Git locale. Questo comando è un ottimo modo per visualizzare graficamente dove si sono verificate divergenze nel repository locale.

**i Nota**

È necessario installare il pacchetto gitk sul sistema di sviluppo per utilizzare questo comando.

- *git log*: Mostra la cronologia dei commit effettuati nel repository. Questo report elenca tutti i commit, indipendentemente dal fatto che siano stati inviati al repository remoto o meno.
- *git grep*: Cerca pattern specifici nei file tracciati nella directory di lavoro, nei blob registrati nella directory di lavoro o nei blob presenti in determinati oggetti della directory.
- *git diff*: Visualizza le differenze riga per riga tra un file di lavoro locale e lo stesso file interpretato da Git. Questo comando è utile per vedere le modifiche apportate a un determinato file.
- *git clean*: Pulisce la directory di lavoro rimuovendo ricorsivamente i file non sotto controllo di versione, a partire dalla directory corrente.

- *git reset*: Reimposta l'HEAD corrente allo stato specificato.

## 4.2.6 Licenze

Poiché i progetti open source sono aperti al pubblico, hanno diverse strutture di licenza. L'evoluzione delle licenze sia per l'open source che per il software libero ha una storia interessante. Se siete interessati a questa storia, potete trovare informazioni di base qui:

- [Open source license history](#)
- [Free software license history](#)

In generale, Yocto Project è ampiamente distribuito con la licenza del Massachusetts Institute of Technology (MIT). La licenza MIT consente il riutilizzo del software all'interno di software proprietario, a condizione che la licenza sia distribuita insieme al software stesso. Le patch per Yocto Project seguono lo schema di licenza upstream. Si possono trovare informazioni sulla licenza MIT [qui](#).

Quando si crea un'immagine utilizzando Yocto Project, il processo di compilazione utilizza un elenco noto di licenze per garantire la conformità. È possibile trovare questo elenco in *OpenEmbedded-Core (OE-Core)* in [meta/files/common-licenses](#). Una volta completata la compilazione, l'elenco di tutte le licenze trovate e utilizzate durante tale compilazione viene conservato nella *Build Directory* in `tmp/depot/licenses`.

Se un modulo richiede una licenza non presente nell'elenco di base, il processo di compilazione genera un warning durante la compilazione. Questi strumenti facilitano agli sviluppatori la verifica delle licenze a cui i loro prodotti distribuiti devono essere conformi. Tuttavia, anche con questi strumenti, spetta comunque allo sviluppatore risolvere eventuali problemi di licenza.

L'elenco di base delle licenze utilizzate dal processo di compilazione è una combinazione dell'elenco Software Package Data Exchange (SPDX) e dei progetti Open Source Initiative (OSI). [SPDX Group](#) è un gruppo di lavoro della Linux Foundation che si occupa di definire una specifica per un formato standard di comunicazione dei componenti, delle licenze e dei diritti d'autore associati a un pacchetto software. [OSI](#) è un'organizzazione dedicata alla Open Source Definition (OSD) e all'attività di revisione e approvazione delle licenze conformi a tale definizione.

È possibile trovare un elenco delle licenze SPDX e OSI utilizzate dallo Yocto Project nella directory [meta/files/common-licenses](#) all'interno di *OpenEmbedded-Core (OE-Core)*.

Per informazioni che possono aiutare a mantenere la conformità con le varie licenze open source durante il ciclo di vita di un prodotto creato utilizzando Yocto Project, consultare la sezione "[Maintaining Open Source License Compliance During Your Product's Lifecycle](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

## 4.3 Concetti di Yocto Project

Questo capitolo fornisce spiegazioni sui concetti di Yocto Project che vanno oltre le semplici istruzioni pratiche e il materiale di riferimento. Vengono illustrati concetti come i componenti, il *OpenEmbedded Build System* workflow, le toolchain di "cross-development", la cache di stato condivisa [shared] e così via.

### Nota

In questa sezione vengono introdotte numerose variabili e i relativi significati. Se, nel contesto di una directory di compilazione (*Build Directory*), si desidera esaminare il valore di una di queste variabili, è possibile utilizzare il comando `bitbake-getvar`, descritto nella sezione "*Viewing Variable Values*".

### 4.3.1 Componenti di Yocto Project

L'esecutore di attività [task], *BitBake*, insieme a vari tipi di file di configurazione, costituisce il *OpenEmbedded-Core* (*OE-Core*). Questa sezione offre una panoramica di questi componenti, descrivendone l'utilizzo e le interazioni.

BitBake gestisce l'analisi e l'esecuzione dei file di dati. I dati stessi sono di vario tipo:

- *Ricette*: Forniscono dettagli su specifiche parti software.
- *Dati di Classe*: Astraggono le informazioni di build comuni (ad esempio, come compilare un kernel Linux).
- *Dati di Configurazione*: Definiscono le impostazioni specifiche della macchina, le decisioni relative alle policy e così via. I dati di configurazione fungono da collante per unire tutti gli elementi.

BitBake sa come combinare più fonti di dati e si riferisce a ciascuna fonte di dati come a un livello (layer). Per informazioni sui layer, consultare la sezione "*Comprendere e Creare i Layer*" del Manuale di Sviluppo dei Task di Yocto Project.

Ecco alcuni brevi dettagli su questi componenti principali. Per ulteriori informazioni su come questi componenti interagiscono durante una compilazione, consultare la sezione "*Concetti del Sistema di Build OpenEmbedded*".

#### BitBake

BitBake è lo strumento centrale di *OpenEmbedded Build System* e si occupa di analizzare i *Metadata*, generare un elenco di attività [task] e quindi eseguirle.

Questa sezione introduce brevemente BitBake. Per ulteriori informazioni su BitBake, consultare il [Manuale Utente di BitBake](#).

Per visualizzare un elenco delle opzioni supportate da BitBake, utilizzare uno dei seguenti comandi:

```
$ bitbake -h
$ bitbake --help
```

L'utilizzo più comune di BitBake è `bitbake recipename`, dove `recipename` è il nome della ricetta che si desidera compilare (indicato come "target"). Il target spesso corrisponde alla prima parte del nome del file di una ricetta (ad esempio, "foo" per un file di ricetta denominato `foo_1.3.0.bb`). Quindi, per elaborare il file di ricetta `matchbox-desktop_1.2.3.bb`, si digita quanto segue:

```
$ bitbake matchbox-desktop
```

Potrebbero esistere diverse versioni di `matchbox-desktop`. BitBake sceglie quella selezionata dalla configurazione della distribuzione. Maggiori dettagli su come BitBake sceglie tra le diverse versioni e provider di destinazione nella sezione "*Preferences*" del Manuale Utente di BitBake.

BitBake tenta inoltre di eseguire prima tutti i task dipendenti. Ad esempio, prima di compilare `matchbox-desktop`, BitBake compilerebbe un cross-compilatore e `glibc` se non fossero già stati compilati.

Un'opzione utile di BitBake da considerare è `-k o --continue`. Questa opzione indica a BitBake di tentare di continuare l'elaborazione del job il più a lungo possibile anche dopo aver riscontrato un errore. Quando si verifica un errore, il target che ha fallito e quelli che dipendono da esso non possono essere ricreati. Tuttavia, quando si utilizza questa opzione, le altre dipendenze possono comunque essere elaborate.

## Ricette

I file con estensione `.bb` sono "ricette". In generale, una ricetta contiene informazioni su un singolo software. Queste informazioni includono la posizione da cui scaricare il codice sorgente non modificato, eventuali patch da applicare al codice sorgente (se necessario), le opzioni di configurazione speciali da applicare, le modalità di compilazione dei file sorgente e le modalità di creazione del pacchetto dell'output compilato.

Il termine "package" [pacchetto] viene talvolta utilizzato per riferirsi alle ricette. Tuttavia, poiché il termine "package" viene utilizzato per indicare l'output impacchettato dal sistema di build OpenEmbedded (ovvero i file `.ipk`, `.deb` o `.rpm`), in questo documento si evita di utilizzare il termine "package" quando ci si riferisce alle ricette.

## Classi

I file di classe (`.bbclass`) contengono informazioni utili da condividere tra i file di ricetta. Un esempio è la classe *autotools\**, che contiene impostazioni comuni per qualsiasi applicazione compilata con GNU Autotools. Il capitolo "Classi" nel Manuale di Riferimento di Yocto Project.

## Configurazioni

I *file di configurazione* (`.conf`) definiscono diverse variabili di configurazione che regolano il processo di build di OpenEmbedded. Questi file rientrano in diverse aree che definiscono opzioni di configurazione della macchina, opzioni di configurazione della distribuzione, opzioni di ottimizzazione del compilatore, opzioni di configurazione comuni generali e opzioni di configurazione utente in *build/conf/local.conf*, che si trova nella *Build Directory*.

### 4.3.2 Layer

I layer sono repository che contengono metadati correlati (ovvero insiemi di istruzioni) che indicano al sistema di build OpenEmbedded come compilare un target. *Il Modello a Layer di Yocto Project* facilita la collaborazione, la condivisione, la personalizzazione e il riutilizzo all'interno dell'ambiente di sviluppo di Yocto Project. I layer separano logicamente le informazioni per il progetto. Ad esempio, si può utilizzare un layer per contenere tutte le configurazioni per un particolare componente hardware. Isolare le configurazioni specifiche dell'hardware consente di condividere altri metadati utilizzando un layer diverso laddove tali metadati potrebbero essere comuni a più componenti hardware.


Nell'ambiente di sviluppo di Yocto Project sono presenti numerosi layer. Lo *Yocto Project Compatible Layer Index* e *OpenEmbedded Layer Index* contengono entrambi layer utilizzabili o sfruttabili.

Per convenzione, i layer in Yocto Project seguono una struttura specifica. Conformarsi a una struttura nota consente a BitBake di fare delle ipotesi durante la compilazione su dove trovare i diversi tipi di metadati. È possibile trovare procedure e informazioni sugli strumenti (ad esempio `bitbake-layers`) per la creazione di layer adatti a Yocto Project nella sezione "*Comprendere e Creare i Layer*" del Manuale di Sviluppo dei Task di Yocto Project.

### 4.3.3 Concetti del Sistema di Build OpenEmbedded

Questa sezione analizza in dettaglio il processo di build utilizzato dall'*OpenEmbedded Build System*, specifico di Yocto Project. Il cuore del sistema di build è BitBake, l'esecutore delle task.

Il diagramma seguente rappresenta il flusso di lavoro di alto livello di una build. Il resto di questa sezione approfondisce i blocchi logici fondamentali di input, output, processo e metadati che costituiscono il flusso di lavoro [workflow].




In generale, il flusso di lavoro di una build è composto da diverse aree funzionali:

- *Configurazione Utente*: Metadati utilizzabili per controllare il processo di build.
- *Layer di metadati*: Vari layer che forniscono metadati relativi a software, macchine e distribuzioni.
- *File Sorgente*: Release upstream, progetti locali e sistemi di controllo versione (SCM).
- *Sistema di Build*: Processi controllati da *BitBake*. Questo blocco illustra in dettaglio come BitBake recupera il codice sorgente, applica le patch, completa la compilazione, analizza l'output per la generazione dei pacchetti, crea e testa i pacchetti, genera le immagini e crea gli strumenti di sviluppo incrociato [cross].
- *Flussi di Pacchetti*: Directory contenenti i pacchetti di output (RPM, DEB o IPK), che vengono successivamente utilizzati per la creazione di un'immagine o di un Software Development Kit (SDK) prodotti dal sistema di build. Questi flussi possono anche essere copiati e condivisi tramite un server web o altri mezzi per facilitare l'estensione o l'aggiornamento delle immagini esistenti sui dispositivi in fase di esecuzione, se la gestione dei pacchetti in fase di esecuzione è abilitata.
- *Immagini*: Immagini prodotte dal flusso di lavoro.
- *SDK per lo Sviluppo di Applicazioni*: Strumenti di cross-sviluppo prodotti insieme a un'immagine o separatamente con BitBake.

#### Configurazione Utente

La configurazione utente aiuta a definire la build. Tramite la configurazione utente, è possibile indicare a BitBake l'architettura di destinazione [target] per la quale si sta creando l'immagine, la posizione in cui archiviare il codice sorgente scaricato e altre proprietà della build.

La figura seguente mostra una rappresentazione ingrandita della casella "User Configuration" della *della figura del flusso di lavoro generale*:



BitBake necessita di alcuni file di configurazione di base per completare una build. Questi file sono file `*.conf`. Quelli minimi necessari si trovano come file di esempio nella sottocartella `conf` della *Build Directory*.

Quando si *inizializza l'ambiente di build*, è possibile specificare quale directory sarà la *Source Directory*.

La configurazione dell'ambiente di compilazione crea una *Build Directory* se non esiste già. BitBake utilizza questa *Build Directory* per tutte le sue operazioni durante la compilazione. La Build Directory contiene una sottodirectory `conf` che include le versioni di default dei file di configurazione *build/conf/local.conf* e *build/conf/bblayers.conf* *configuration files*. Questi *file di configurazione* di default vengono creati solo se non sono già presenti nella *Build Directory* al momento dell'esecuzione dello script di configurazione dell'ambiente di compilazione.

I *File di configurazione* forniscono numerose variabili di base che definiscono un ambiente di build. Per visualizzare un elenco delle possibili variabili per configurare tramite i *file di configurazione*, consultare il file `local.conf.sample` in *OpenEmbedded-Core (OE-Core)*:

Ecco un elenco non esaustivo:

- *Selezione della Macchina Target*: Controllata dalla variabile `MACHINE`.
- *Directory di Download*: Controllata dalla variabile `DL_DIR`.
- *Directory Shared State*: Controllata dalla variabile `SSTATE_DIR`.
- *Directory dei Dati Persistenti*: Controllata dalla variabile `PERSISTENT_DIR`.
- *Output della Build*: Controllata dalla variabile `TMPDIR`.
- *Policy di Distribuzione*: Controllata dalla variabile `DISTRO`.
- *Formato del Packaging*: Controllato dalla variabile `PACKAGE_CLASSES`.
- *Architettura Target dell'SDK*: Controllata dalla variabile `SDKMACHINE`.
- *Pacchetti Extra dell'Immagine*: Controllati dalla variabile `EXTRA_IMAGE_FEATURES`.



**i Nota**

Le configurazioni impostate nel file `build/conf/local.conf` possono essere impostate anche nei file di configurazione `build/conf/site.conf` e `build/conf/auto.conf`.

Il file `build/conf/bblayers.conf` indica a BitBake quali layer considerare durante la compilazione. Per default, i layer elencati in questo file includono quelli minimi necessari al sistema di compilazione. Tuttavia, è necessario aggiungere manualmente eventuali layer personalizzati creati. Ulteriori informazioni sull'utilizzo del file `build/conf/bblayers.conf` sono disponibili nella sezione "*Enabling Your Layer*" nel Manuale di Sviluppo dei Task di Yocto Project.

I file `site.conf` e `build/conf/auto.conf` non vengono creati dallo script di inizializzazione dell'ambiente. Se si desidera il file `build/conf/auto.conf`, lo si deve creare manualmente. Il file `build/conf/auto.conf` viene in genere creato da un autobuilder:

- *site.conf*: Si può utilizzare il file di configurazione `build/conf/site.conf` per configurare più directory di build. Ad esempio, supponiamo di avere diversi ambienti di build che condividono alcune caratteristiche comuni. Si possono impostare queste proprietà di build predefinite qui. Un buon esempio potrebbe essere il formato di packaging da utilizzare tramite la variabile `PACKAGE_CLASSES`.
- *auto.conf*: Il file viene solitamente creato e modificato da un autobuilder. Le impostazioni inserite nel file sono in genere le stesse che si troverebbero nei file `build/conf/local.conf` o `build/conf/site.conf`.

È possibile modificare tutti i file di configurazione per definire ulteriormente un ambiente di compilazione specifico. Questo processo è rappresentato dal riquadro "User Configuration Edits" nella figura.

Quando si avvia la build col comando `bitbake target`, BitBake elabora le configurazioni per definire l'ambiente di build. È importante capire che *OpenEmbedded Build System* legge i file di configurazione in un ordine specifico: `site.conf`, `build/conf/auto.conf` e `build/conf/local.conf`. Inoltre, il sistema di build applica le normali regole di assegnazione delle istruzioni come descritto nel capitolo "*Syntax and Operators*" del Manuale Utente di BitBake. Poiché i file vengono analizzati in un ordine specifico, le assegnazioni di variabili per la stessa variabile potrebbero essere influenzate. Ad esempio, se il file `build/conf/auto.conf` e il file `local.conf` assegnano valori diversi alla variabile `l`, poiché il sistema di compilazione analizza `build/conf/local.conf` dopo `build/conf/auto.conf`, alla variabile `l` viene assegnato il valore presente nel file `build/conf/local.conf`.

## Metadati, Configurazione della Macchina e Configurazione delle Policy

La sezione precedente ha descritto le configurazioni utente che definiscono il comportamento globale di BitBake. Questa sezione esamina più da vicino i layer utilizzati dal sistema di build per controllare ulteriormente il processo di build. Questi layer forniscono metadati per il software, la macchina e le policy.

In generale, esistono tre tipi di input per i layer. È possibile visualizzarli sotto la casella "User Configuration" nella figura del *flusso di lavoro generale*:


- *Metadata (.bb + Patches)*: Layer software contenenti file di ricette, patch e file di append forniti dall'utente. Un buon esempio di layer software potrebbe essere il layer `meta-qt5` layer dall' *OpenEmbedded Layer Index*. Questo layer è per la versione 5.0 del popolare framework di sviluppo di applicazioni multiplatforma Qt per desktop, sistemi embedded e dispositivi mobili.
- *Configurazione BSP della Macchina*: I layer del Board Support Package (BSP) (ovvero "BSP Layer" nella figura seguente) forniscono configurazioni specifiche per la macchina. Questo tipo di informazioni è specifico per una



particolare architettura target . Un buon esempio di layer BSP dalla *Distribuzione Embedded di Riferimento (Poky)* è il layer `meta-yocto-bsp`.

- *Configurazione delle Policy*: I layer di distribuzione (ovvero "Distro Layer" nella figura seguente) forniscono policy di alto livello o generali per le immagini o gli SDK che vengono compilati per una particolare distribuzione. Ad esempio, nella Poky Reference Distribution, il layer della distro è `meta-poky`. All'interno del layer distro è presente una directory `conf/distro` che contiene i file di configurazione della distribuzione (ad esempio, `poky.conf` che contengono numerose configurazioni di policy per la distribuzione *Poky*.

La figura seguente mostra una rappresentazione estesa di questi tre layer, tratta dalla *figura del flusso di lavoro generale*:



In generale, tutti i layer hanno una struttura simile. Contengono tutti un file di licenza (ad esempio, `COPYING.MIT`) se il layer deve essere distribuito, un file `README` come buona prassi e soprattutto se il layer deve essere distribuito, una directory di configurazione e directory di ricette. È possibile trovare informazioni sulla struttura generale dei layer utilizzati con Yocto Project nella sezione *"Creating Your Own Layer"* nel Manuale di Sviluppo dei Task di Yocto Project. Per una discussione generale sui layer e sui numerosi layer da cui è possibile attingere, consultare le sezioni *"Layer"* e *"Il Modello a Layer di Yocto Project"* presenti in precedenza in questo manuale.

Esplorando i link precedenti, avrete scoperto alcune aree in cui sono presenti molti layer compatibili con Yocto Project. Anche i *Source Repositories* mostrano i layer categorizzati sotto "Yocto Metadata Layers".

#### **Nota**

Nei Repository del Codice Sorgente di Yocto Project sono presenti layer che non si trovano nell'indice dei layer di OpenEmbedded. Tali layer sono obsoleti o sperimentali.

BitBake utilizza il file `build/conf/bblayers.conf`, che fa parte della configurazione utente, per individuare i layer da utilizzare durante la compilazione.

## Layer Distro

Un layer di distribuzione fornisce le configurazioni delle policy per la distribuzione. Le best practice suggeriscono di isolare questo tipo di configurazioni in un layer dedicato. Le impostazioni che si forniscono in `conf/distro/distro.conf` sovrascrivono le impostazioni simili che BitBake trova nel file `build/conf/local.conf` nella directory *Build Directory*.

Il seguente elenco fornisce alcune spiegazioni e riferimenti su ciò che si trova tipicamente in un layer di distribuzione (ricordare che `meta-poky` è un tale layer):

- *classes, classes-global, classes-recipe*: I file di classe (`.bbclass`) contengono funzionalità comuni che possono essere condivise tra le ricette nella distribuzione. Quando le ricette ereditano una classe, ne assumono le impostazioni e le funzioni. Per ulteriori informazioni sui file di classe, consultare il capitolo "*Classi*" del Manuale di Riferimenti di Yocto.
- *conf*: Questa area contiene i file di configurazione per il layer (`conf/layer.conf`), la distribuzione (`conf/distro/distro.conf`) e tutti i file di inclusione a livello di distribuzione.
- *recipes-\**: Ricette e file di append che influenzano le funzionalità comuni a tutta la distribuzione. Quest'area potrebbe includere ricette e file di append per aggiungere configurazioni specifiche della distribuzione, script di inizializzazione, ricette di immagini personalizzate e così via. Esempi di directory `recipes-*` sono `recipes-core` e `recipes-extra`. La gerarchia e il contenuto all'interno di una directory `recipes-*` possono variare. In genere, queste directory contengono file di ricette (`*.bb`), file di aggiunta alle ricette (`*.bbappend`), directory specifiche della distribuzione per i file di configurazione e così via.

## Layer BSP

Un layer BSP fornisce configurazioni macchina destinate a hardware specifici. Tutto ciò che si trova in questo layer è specifico per la macchina per la quale si sta creando l'immagine o l'SDK. Per i layer BSP è definita una struttura o un formato comune. È possibile trovare maggiori informazioni su questa struttura nel manuale *Manuale del Board Support Package (BSP) di Yocto Project*.

### Nota

Affinché un layer BSP sia considerato conforme allo Yocto Project, deve soddisfare alcuni requisiti strutturali.

La directory di configurazione di un layer BSP contiene i file di configurazione per la macchina (`conf/machine/machine.conf`) e, naturalmente, per il layer stesso (`conf/layer.conf`).

La parte restante del layer è dedicata a ricette specifiche per funzione: `recipes-bsp`, `recipes-core`, `recipes-graphics`, `recipes-kernel` e così via. Possono essere presenti metadati per più fattori di forma, sistemi di supporto grafico e altro ancora.

**i Nota**

Sebbene la figura mostri diverse directory `recipes-*`, non tutte queste directory compaiono in tutti i livelli BSP.

## Layer Software

Un layer software fornisce i metadati per i pacchetti software aggiuntivi utilizzati durante la compilazione. Questo layer non include i metadati specifici della distribuzione o della macchina, che si trovano nei rispettivi layer.

Questo layer contiene tutte le ricette, i file di append e le patch necessarie al progetto.

## Sorgenti

Affinché il sistema di build OpenEmbedded possa creare un'immagine o qualsiasi target, deve essere in grado di accedere ai file sorgente. La *figura del flusso di lavoro generale* rappresenta i file sorgente utilizzando i riquadri "Upstream Project Releases", "Local Projects" E "SCMs (optional)". La figura rappresenta anche i mirror, che svolgono un ruolo nell'individuazione dei file sorgente, con il riquadro "Source Materials".


Il metodo con cui i file sorgente vengono organizzati dipende dal progetto. Ad esempio, per il software rilasciato, i progetti tendono a utilizzare tarball o altri file archiviati che catturano lo stato di una release, garantendone una rappresentazione statica. D'altra parte, per un progetto più dinamico o sperimentale, i file sorgente potrebbero essere conservati in un repository gestito da un Source Control Manager (SCM) [sistema di controllo versione] come Git. Scaricare il codice sorgente da un repository consente di controllare il punto di partenza (la revisione) da cui si desidera compilare il software. È anche possibile una combinazione dei due metodi.

BitBake utilizza la variabile `SRC_URI` per indicare la posizione dei file sorgente, indipendentemente dalla loro ubicazione. Ogni ricetta deve avere una variabile `SRC_URI` che punta al codice sorgente.

Un altro elemento che gioca un ruolo significativo nella provenienza dei file sorgente è indicato dalla variabile `DL_DIR`. Questa area è una cache che può contenere il codice sorgente scaricato in precedenza. È anche possibile istruire il sistema di build OpenEmbedded a creare tarball dai repository Git, il che non è il comportamento di default, e a memorizzarli nella directory `DL_DIR` utilizzando la variabile `BB_GENERATE_MIRROR_TARBALLS`.

Un uso oculato della directory `DL_DIR` può evitare al sistema di build di dover effettuare una ricerca su Internet per trovare i file. Un buon metodo per utilizzare una directory di download è quello di impostare `DL_DIR` in modo che punti a un'area esterna alla directory *Build Directory*. In questo modo è possibile eliminare in sicurezza la directory *Build Directory* se necessario, senza il rischio di rimuovere i file sorgente scaricati.

Il resto di questa sezione fornisce un'analisi più approfondita dei file sorgente e dei mirror. Ecco una descrizione più dettagliata dell'area dei file sorgente nella *figura del flusso di lavoro generale*:



## Versioni dei Progetti Upstream

Le versioni dei progetti upstream sono disponibili ovunque sotto forma di file compressi (ad esempio, file tarball o zip). Questi file corrispondono a singole ricette. Ad esempio, la figura utilizza versioni specifiche per BusyBox, Qt e Dbus. Un file di archivio può essere relativo a qualsiasi prodotto rilasciato che può essere compilato utilizzando una ricetta.

## Progetti Locali

I progetti locali sono porzioni di software personalizzate fornite dall'utente. Queste porzioni risiedono in una posizione locale al progetto, ad esempio una directory in cui l'utente carica i file (come una directory locale contenente la struttura di directory del codice sorgente utilizzata dal gruppo).

Il metodo canonico per includere un progetto locale consiste nell'utilizzare la classe *externalsrc*. È possibile utilizzare il file *build/conf/local.conf* o il file append di una ricetta per sovrascrivere o impostare la ricetta in modo che punti alla directory locale da cui recuperare il codice sorgente.

## Gestori di Controllo Versione (opzionale)

Un'altra fonte da cui il sistema di build può ottenere i file sorgente è tramite [Fetchers](#), utilizzando diversi Source Control Managers (SCM) come Git o Subversion. In questi casi, un repository viene clonato o estratto. Il task `do_fetch` all'interno di BitBake utilizza la variabile `SRC_URI` e il prefisso dell'argomento per determinare il modulo fetcher corretto.

### Nota

Per informazioni su come fare in modo che il sistema di build OpenEmbedded generi tarball per i repository Git e li posizioni nella directory `DL_DIR`, consultare la variabile `BB_GENERATE_MIRROR_TARBALLS` nel Manuale di Riferimento di Yocto Project.

Quando recupera un repository, BitBake utilizza la variabile `SRCREV` per determinare la revisione specifica da cui effettuare la compilazione.

## Mirror del Codice Sorgente


Esistono due tipi di mirror: pre-mirror e mirror standard. Le variabili `PREMIRRORS` e `MIRRORS` puntano rispettivamente a questi due tipi. BitBake controlla i pre-mirror prima di cercare i file sorgente nel repository principale. I pre-mirror sono appropriati quando si dispone di una directory condivisa che non è definita dalla variabile `DL_DIR`. Un pre-mirror in genere punta a una directory condivisa locale all'organizzazione.

I mirror standard possono essere qualsiasi sito su Internet utilizzato come posizione alternativa per il codice sorgente nel caso in cui il sito principale non sia funzionante per un motivo o per l'altro.

## Feed dei Pacchetti

Quando il sistema di build OpenEmbedded genera un'immagine o un SDK, preleva i pacchetti da un'area di feed [alimentazione] di pacchetti situata nella *Build Directory*. La *figura del flusso di lavoro generale* mostra quest'area di feed di pacchetti nell'angolo in alto a destra.

Questa sezione esamina più nel dettaglio l'area di feed di pacchetti utilizzata dal sistema di compilazione. Ecco una descrizione più approfondita dell'area:



I feed di pacchetti sono una fase intermedia del processo di build. Il sistema di build OpenEmbedded fornisce classi per generare diversi tipi di pacchetti e si specificano le classi da abilitare tramite la variabile `PACKAGE_CLASSES`. Prima di inserire i pacchetti nei feed, il processo di compilazione li convalida con i controlli di qualità dell'output generati tramite la classe `insane`.

L'area di feed di pacchetti si trova nella *Build Directory*. La directory utilizzata dal sistema di build per memorizzare temporaneamente i pacchetti è determinata da una combinazione di variabili e dal gestore di pacchetti in uso. Consultare il riquadro "Package Feeds" nell'illustrazione e le informazioni a destra di tale area. In particolare, quanto segue definisce la posizione in cui vengono conservati i file dei pacchetti:

- `DEPLOY_DIR`: Definita come `tmp/deploy` nella *Build Directory*.
- `DEPLOY_DIR_*`: A seconda del gestore di pacchetti utilizzato, la sottocartella del tipo di pacchetto. In caso di creazione di pacchetti RPM, IPK o DEB e di archivi tarball, vengono utilizzate rispettivamente le variabili `DEPLOY_DIR_RPM`, `DEPLOY_DIR_IPK` o `DEPLOY_DIR_DEB`.
- `PACKAGE_ARCH`: Definisce le sottocartelle specifiche dell'architettura. Ad esempio, potrebbero essere disponibili pacchetti per le architetture `i586` o `qemux86`.

BitBake utilizza i task `do_package_write_*` per generare pacchetti e posizzionarli nell'area di gestione dei pacchetti (ad esempio, `do_package_write_ipk` per i pacchetti IPK). Per ulteriori informazioni, consultare le sezioni "`do_package_write_deb`", "`do_package_write_ipk`" e "`do_package_write_rpm`" nel Manuale di Riferimento di Yocto Project. Ad esempio, si consideri uno scenario in cui viene utilizzato un gestore di pacchetti IPK e sono disponibili architetture di pacchetti sia per `i586` che per `qemux86`. I pacchetti per l'architettura `i586` vengono posizionati in `build/tmp/deploy/ipk/i586`, mentre i pacchetti per l'architettura `qemux86` vengono posizionati in `build/tmp/deploy/ipk/qemux86`.

## Il Tool BitBake


Il sistema di build di OpenEmbedded utilizza *BitBake* per produrre immagini e Software Development Kit (SDK). Come si può vedere nella *figura del flusso di lavoro generale*, l'area BitBake è composta da diverse aree funzionali. Questa sezione esamina più nel dettaglio ciascuna di queste aree.

### **i** Nota

La documentazione per il tool BitBake è disponibile separatamente. Consultare il [Manuale Utente di BitBake](#) per materiale di riferimento su BitBake.

## Prelievo del Codice Sorgente

Le prime fasi della creazione di una ricetta consistono nel recuperare [fetch] e spaccettare il codice sorgente:



I task *do\_fetch* e *do\_unpack* recuperano i file sorgente e li decomprimono nella *Build Directory*.

**i Nota**

Per ogni file locale (ad esempio `file://`) che fa parte dell'istruzione `SRC_URI` di una ricetta, il sistema di build OpenEmbedded calcola il checksum del file per la ricetta e lo inserisce nella firma [signature] del task `do_fetch`. Se un file locale è stato modificato, il task `do_fetch` e tutti quelli che dipendono da esso vengono rieseguiti.

Per default, tutto viene eseguito nella *Build Directory*, che ha una struttura definita. Per ulteriori informazioni generali sulla *Build Directory*, consultare la sezione "*build*" nel Manuale di Riferimento di Yocto Project.

Ogni ricetta ha un'area nella *Build Directory* in cui risiede il codice sorgente decompresso. La variabile `UNPACKDIR` punta a questa area per il codice sorgente decompresso di una ricetta e ha come nome di default `sources`. La figura precedente e l'elenco seguente descrivono la gerarchia della *Build Directory*:

- `TMPDIR`: La directory base in cui il sistema di build OpenEmbedded esegue tutte le sue operazioni durante la compilazione. La directory base di default è `tmp`.
- `PACKAGE_ARCH`: L'architettura del pacchetto o dei pacchetti compilati. A seconda della destinazione finale del pacchetto o dei pacchetti (ad esempio, architettura della macchina, *Build Host*, SDK o macchina specifica), `PACKAGE_ARCH` varia. Per ulteriori dettagli, consultare la descrizione della variabile.
- `TARGET_OS`: Il sistema operativo del dispositivo target. Un valore tipico è "linux" (ad esempio, "qemux86-poky-linux").
- `PN`: Il nome della ricetta utilizzata per creare il pacchetto. Questa variabile può avere diversi significati. Tuttavia, quando utilizzata nel contesto dei file di input, `PN` rappresenta il nome della ricetta.
- `WORKDIR`: La directory in cui il sistema di build OpenEmbedded crea una ricetta (ovvero, esegue le operazioni necessarie per creare il pacchetto).
  - `PV`: La versione della ricetta utilizzata per creare il pacchetto.
- `UNPACKDIR`: Contiene i file sorgente decompressi per una determinata ricetta.
- `S`: Contiene la posizione finale del codice sorgente.

Il valore si default per `BP` è `${BPN}-${PV}` dove:

- `BPN`: Il nome della ricetta utilizzata per creare il pacchetto. La variabile `BPN` è una versione della variabile `PN` ma senza prefissi e suffissi comuni.
- `PV`: La versione della ricetta utilizzata per creare il pacchetto.




**Nota**

Nella figura precedente, si noti che sono presenti due gerarchie di esempio: una basata sull'architettura del pacchetto (ovvero *PACKAGE\_ARCH*) e una basata sulla macchina (ovvero *MACHINE*). Le strutture sottostanti sono identiche. La differenza risiede nell'elemento utilizzato dal sistema di build OpenEmbedded come target di compilazione (ad esempio, architettura generale, host di compilazione, SDK o una macchina specifica).

## Applicazione delle Patch

Una volta scaricato ed estratto il codice sorgente, BitBake individua i file di patch e li applica ai file sorgente:



Il task `do_patch` utilizza le istruzioni `SRC_URI` di una ricetta e la variabile `FILES_PATH` per individuare i file di patch applicabili.

L'elaborazione di default dei file di patch presuppone che i file abbiano estensione `*.patch` o `*.diff` (o una versione compressa di tali estensioni). È possibile utilizzare i parametri `SRC_URI` per modificare il modo in cui il sistema di build riconosce i file di patch. Per ulteriori informazioni, consultare il task `do_patch`.


BitBake individua e applica più patch per una singola ricetta nell'ordine in cui le individua. La variabile `FILES_PATH` definisce l'insieme predefinito di directory che il sistema di build utilizza per cercare i file di patch. Una volta individuate, le patch vengono applicate ai file sorgente della ricetta, che si trovano nella directory `S`.

Per ulteriori informazioni su come vengono create le directory dei sorgenti, consultare la sezione "[Prelievo del Codice Sorgente](#)". Per ulteriori informazioni su come creare le patch e su come il sistema di compilazione le elabora, consultare la sezione "[Patching Code](#)" nel Manuale di Sviluppo dei Task di Yocto Project. È inoltre possibile consultare la

sezione "*Use devtool modify to Modify the Source of an Existing Component*" nel Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK) e la sezione "*Using Traditional Kernel Development to Patch the Kernel*" nel Manuale di Sviluppo del Kernel Linux di Yocto Project.

## Configurazione, Compilazione e Staging

Dopo l'applicazione delle patch al codice sorgente, BitBake esegue dei task di configurazione e compilazione. Una volta completata la compilazione, i file vengono copiati in un'area temporanea (staging) in preparazione per il packaging:



Questa fase del processo di build comprende le seguenti attività [task]:

- *do\_prepare\_recipe\_sysroot*: Questo task configura le due directory di sistema (sysroot) nella directory `${WORKDIR}` (ovvero `recipe-sysroot` e `recipe-sysroot-native`) in modo che i task successivi della ricetta (in particolare *do\_configure* e *do\_compile*) possano accedere alle librerie, ai file header e ad altri file simili creati dalle ricette da cui dipende.
  - `recipe-sysroot`: contiene le librerie target, i relativi file header e altri dati necessari per la cross-compilazione del software a partire dai suoi sorgenti
  - `recipe-sysroot-native`: contiene eseguibili nativi dell'host con le relative librerie e altri dati, in modo che possano essere eseguiti direttamente sull'host di build quando richiesto dal processo di compilazione.

- *do\_configure*: Questo task configura il codice sorgente abilitando e disabilitando le opzioni di configurazione e di fase di compilazione per il software in fase di build. Le configurazioni possono provenire dalla ricetta stessa, così come da una classe ereditata. Inoltre, il software stesso potrebbe configurarsi a seconda del target per cui viene compilato.


Le configurazioni gestite dal task *do\_configure* sono specifiche per le configurazioni del codice sorgente compilato dalla ricetta.

Se si utilizza la classe *autotools\**, è possibile aggiungere ulteriori opzioni di configurazione tramite le variabili *EXTRA\_OECONF* o *PACKAGECONFIG\_CONFARGS*. Per informazioni sul funzionamento di queste variabili all'interno della classe, consultare la documentazione della classe *autotools\** [qui](#).

- *do\_compile*: Una volta completato un task di configurazione, BitBake compila il codice sorgente utilizzando il task *do\_compile*. La compilazione avviene nella directory indicata dalla variabile *B*. Si noti che la directory *B* è, per default, la stessa della directory *S*.
- *do\_install*: Al termine della compilazione, BitBake esegue il task *do\_install*. Questo task copia i file dalla directory *B* e li posiziona in un'area temporanea indicata dalla variabile *D*. La creazione del pacchetto avviene successivamente utilizzando i file presenti in questa directory di appoggio.

### Suddivisione in Pacchetti

Dopo che il codice sorgente è stato configurato, compilato e predisposto, il sistema di build analizza i risultati e suddivide l'output in pacchetti:



I task `do_package` e `do_packagedata` vengono utilizzati per analizzare i file presenti nella directory `D` e suddividerli in sottoinsiemi in base ai pacchetti e ai file disponibili. L'analisi include, tra le altre cose, l'estrazione dei simboli di debug, l'esame delle dipendenze delle librerie condivise tra i pacchetti e l'analisi delle relazioni tra i pacchetti.

Il task `do_packagedata` crea i metadati dei pacchetti in base all'analisi, in modo che il sistema di build possa generare i pacchetti finali. Il task `do_populate_sysroot` predispone (copia) un sottoinsieme dei file installati dal task `do_install` nella directory `sysroot` appropriata. I risultati di lavoro, di fase e intermedi del processo di analisi e suddivisione dei pacchetti utilizzano diverse aree:

- **PKGDESTWORK**: Un'area di lavoro temporanea (ovvero `pkgdata`) utilizzata dal task `do_package` per salvare i metadati dei pacchetti.
- **PKGDEST**: La directory di destinazione (ovvero `package`) per i pacchetti prima che vengano suddivisi in singoli pacchetti.

- **PKGDEST**: La directory genitore (ovvero `packages-split`) per i pacchetti dopo che sono stati suddivisi.
- **PKGDATA\_DIR**: Una directory condivisa [shared] a livello globale che contiene i metadati di packaging generati durante il processo di packaging. Tale processo copia i metadati da **PKGDESTWORK** all'area **PKGDATA\_DIR** dove diventano disponibili a livello globale.
- **STAGING\_DIR\_HOST**: Il path della directory di sistema (sysroot) del sistema su cui viene compilato un componente per l'esecuzione (ad esempio, `recipe-sysroot`).
- **STAGING\_DIR\_NATIVE**: Il path della directory di sistema utilizzata per la compilazione dei componenti per l'host di compilazione (ad esempio, `recipe-sysroot-native`).
- **STAGING\_DIR\_TARGET**: Il path della directory di sistema utilizzata quando un componente, compilato per l'esecuzione su un sistema, genera codice per un'altra macchina (ad esempio, le ricette *cross-canadian*).

I pacchetti per una ricetta sono elencati nella variabile **PACKAGES**. Il file di configurazione `bitbake.conf` definisce il seguente elenco predefinito di pacchetti:

```
PACKAGES = "${PN}-src ${PN}-dbg ${PN}-staticdev ${PN}-dev ${PN}-doc ${PN}-locale $
↪{PACKAGE_BEFORE_PN} ${PN}"
```

Ciascuno di questi pacchetti contiene un elenco di default di file definiti con la variabile **FILES**. Ad esempio, il pacchetto `${PN}-dev` rappresenta i file utili allo sviluppo di applicazioni che dipendono da `${PN}`. L'elenco di default di file per `${PN}-dev`, definito anche in `bitbake.conf`, è definito come segue:

```
FILES:${PN}-dev = "${includedir} ${FILES_SOLIBSDEV} ${libdir}/*.la \
                  ${libdir}/*.o ${libdir}/pkgconfig ${datadir}/pkgconfig \
                  ${datadir}/aclocal ${base_libdir}/*.o \
                  ${libdir}/${BPN}/*.la ${base_libdir}/*.la \
                  ${libdir}/cmake ${datadir}/cmake"
```

I path in questo elenco devono essere percorsi *assoluti* dal punto di vista del filesystem root sul target e *non* devono fare riferimento alla variabile **D** o a qualsiasi variabile correlata a **WORKDIR**. Un esempio corretto sarebbe:

```
${sysconfdir}/foo.conf
```

#### Nota

L'elenco dei file per un pacchetto viene definito utilizzando la sintassi di override, separando i **FILES** e il nome del pacchetto con due punti (:).

Un dato file può appartenere a un solo pacchetto. Iterando dal pacchetto più a sinistra a quello più a destra in **PACKAGES**, ogni file che corrisponde a uno dei modelli definiti nella corrispondente definizione di **FILES** viene incluso nel pacchetto.

**i Nota**

Per scoprire quale pacchetto installa un file, è possibile utilizzare l'utilità da riga di comando `oe-pkgdata-util`:

```
$ oe-pkgdata-util find-path '/etc/fstab'
base-files: /etc/fstab
```

Per ulteriori informazioni sull'utilità `oe-pkgdata-util`, consultare la sezione *Viewing Package Information with `oe-pkgdata-util`* del Manuale di Sviluppo dei Task di Yocto Project.

Per aggiungere una variante di pacchetto personalizzata della ricetta `${PN}` denominata `${PN}-extra` (il nome è arbitrario), è possibile aggiungerla alla variabile `PACKAGE_BEFORE_PN`:

```
PACKAGE_BEFORE_PN += "${PN}-extra"
```

In alternativa, un pacchetto personalizzato può essere aggiunto inserendolo nella variabile `PACKAGES` utilizzando l'operatore di prefisso (`=+`):

```
PACKAGES =+ "${PN}-extra"
```


A seconda del tipo di pacchetti creati (RPM, DEB o IPK), il task `do_package_write_*` crea i pacchetti effettivi e li posiziona nell'area del Package Feed, ovvero `${TMPDIR}/deploy`. Per maggiori dettagli su questa parte del processo di build, consultare la sezione *"Feed dei Pacchetti"*.

**i Nota**

Non è previsto il supporto per la creazione di feed direttamente dalle directory `deploy/*`. La creazione di tali feed richiede solitamente un meccanismo di gestione che carichi i nuovi pacchetti in un feed ufficiale (ad esempio, la distribuzione Ångström). Questa funzionalità è fortemente specifica per la distribuzione e pertanto non è disponibile di default.

**Generazione dell'Immagine**

Una volta che i pacchetti sono stati suddivisi e archiviati nell'area Package Feeds, il sistema di build utilizza BitBake per generare l'immagine del filesystem root:



Il processo di generazione dell'immagine si compone di diverse fasi e dipende da diversi task e variabili. Il task *do\_rootfs* crea il filesystem root (struttura di file e directory) per un'immagine. Questo task utilizza diverse variabili chiave per creare l'elenco dei pacchetti da installare:

- *IMAGE\_INSTALL*: Elenca il set base di pacchetti da installare dall'area Package Feeds.
- *PACKAGE\_EXCLUDE*: Specifica i pacchetti che non devono essere installati nell'immagine.
- *IMAGE\_FEATURES*: Specifica le funzionalità da includere nell'immagine. La maggior parte di queste funzionalità corrisponde a pacchetti aggiuntivi da installare.
- *PACKAGE\_CLASSES*: Specifica il backend dei pacchetti (ad esempio RPM, DEB o IPK) da utilizzare e, di conseguenza, aiuta a determinare dove trovare i pacchetti nell'area Package Feeds.
- *IMAGE\_LINGUAS*: Determina la/le lingua/e per cui vengono installati i pacchetti di supporto linguistico aggiuntivi.
- *PACKAGE\_INSTALL*: L'elenco finale dei pacchetti passati al gestore di pacchetti per l'installazione nell'immagine.

Con *IMAGE\_ROOTFS* che punta alla posizione del filesystem in fase di creazione e la variabile *PACKAGE\_INSTALL* che fornisce l'elenco finale dei pacchetti da installare, viene creato il filesystem root.

L'installazione dei pacchetti è gestita dal "package manager" (ad esempio dnf/rpm, opkg o apt/dpkg) indipendentemente dal fatto che la gestione dei pacchetti sia abilitata o meno per il sistema target. Al termine del processo, se la gestione dei pacchetti non è abilitata per il sistema target, i file di dati del gestore di pacchetti vengono eliminati dal filesystem root. Come parte della fase finale dell'installazione dei pacchetti, vengono eseguiti gli script di post-installazione inclusi nei pacchetti stessi. Gli script che non vengono eseguiti correttamente sull'host di build vengono eseguiti sul sistema target al primo avvio. Se si utilizza un filesystem root di sola lettura (vedere *filesystem a sola lettura*, tutti gli script di post-installazione devono essere eseguiti correttamente sull'host di build durante la fase di installazione dei pacchetti, poiché il filesystem root sul sistema di destinazione è di sola lettura.

Le fasi finali del task *do\_rootfs* gestiscono il "post processing". Il post processing include la creazione di un file manifest e le ottimizzazioni.

Il file manifest (*.manifest*) si trova nella stessa directory dell'immagine del filesystem root. Questo file elenca, riga per riga, i pacchetti installati. Il file manifest è utile, ad esempio, per la classe *testimage*, per determinare se eseguire o meno test specifici. Consultare la variabile *IMAGE\_MANIFEST* per ulteriori informazioni.

I processi di ottimizzazione eseguiti sull'immagine includono *mklibs* e qualsiasi altro comando di post-elaborazione definito dalla variabile *ROOTFS\_POSTPROCESS\_COMMAND*. Il processo *mklibs* ottimizza le dimensioni delle librerie.

Dopo la creazione del filesystem root, l'elaborazione dell'immagine inizia tramite il task *do\_image*. Il sistema di compilazione esegue tutti i comandi di pre-elaborazione definiti dalla variabile *IMAGE\_PREPROCESS\_COMMAND*. Questa variabile specifica un elenco di funzioni da chiamare prima che il sistema di compilazione crei i file di output finali dell'immagine.

Il sistema di build crea dinamicamente task *do\_image\_\** secondo necessità, in base ai tipi di immagine specificati nella variabile *IMAGE\_FSTYPES*. Il processo trasforma tutto in un file immagine o in un insieme di file immagine e può comprimere l'immagine del filesystem di root per ridurre le dimensioni complessive. I formati utilizzati per il filesystem di root dipendono dalla variabile *IMAGE\_FSTYPES*. La compressione dipende dal fatto che i formati supportino o meno la compressione.



Ad esempio, un task creato dinamicamente durante la creazione di un particolare tipo di immagine avrebbe la seguente forma:

```
do_image_type
```

Quindi, se il tipo specificato da *IMAGE\_FSTYPES* fosse `ext4`, il task generata dinamicamente sarebbe il seguente:

```
do_image_ext4
```


Il task coinvolto nella creazione dell'immagine è *do\_image\_complete*. Questo task completa l'immagine applicando qualsiasi post-elaborazione definita tramite la variabile *IMAGE\_POSTPROCESS\_COMMAND*. La variabile specifica un elenco di funzioni da chiamare una volta che il sistema di build ha creato i file di output dell'immagine finale.

#### Nota

L'intero processo di generazione dell'immagine viene eseguito in ambiente Pseudo. L'esecuzione in ambiente Pseudo garantisce che i file nel filesystem root abbiano i permessi corretti.

### Generazione dell'SDK

Il sistema di build OpenEmbedded utilizza BitBake per generare gli script di installazione del Software Development Kit (SDK) sia per l'SDK standard che per l'SDK estensibile (eSDK):



### **i** Nota

Per ulteriori informazioni sulla generazione della toolchain di cross-sviluppo, consultare la sezione "[Generazione di Toolchain di Cross-Sviluppo](#)". Per informazioni sui vantaggi derivanti dalla creazione di una toolchain di cross-sviluppo tramite il task `do_populate_sdk`, consultare la sezione "[Building an SDK Installer](#)" in the nel Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (eSDK).

Come per la generazione delle immagini, il processo di creazione degli script SDK si compone di diverse fasi e dipende da numerose variabili. I task `do_populate_sdk` e `do_populate_sdk_ext` utilizzano queste variabili chiave per creare l'elenco dei pacchetti da installare. Per informazioni sulle variabili elencate nella figura, consultare la sezione "[SDK per lo Sviluppo di Applicazioni](#)".

I task `do_populate_sdk` contribuisce alla creazione dell'SDK standard e gestisce due parti: una parte target e una parte host. La parte target è quella compilata per l'hardware target e include librerie e file header. La parte host è la parte dell'SDK che viene eseguita su `SDKMACHINE`.

Il task `do_populate_sdk_ext` contribuisce alla creazione dell'SDK estensibile e gestisce le parti host e target in mo-

do diverso rispetto alla sua controparte per l'SDK standard. Per l'SDK estensibile, il task incapsula il sistema di compilazione, che include tutto il necessario (host e target) per l'SDK.

Indipendentemente dal tipo di SDK in fase di creazione, i task eseguono alcune operazioni di pulizia, dopodiché vengono creati uno script di configurazione dell'ambiente di cross-sviluppo e tutti i file di configurazione necessari. L'output finale è lo script di installazione della toolchain di cross-sviluppo (file `.sh`), che include lo script di configurazione dell'ambiente [environment].

## File Stamp e Riesecuzione dei Task

Per ogni task completata con successo, BitBake scrive un file di "stamp" (timbro) nella directory `STAMPS_DIR`. L'inizio del nome del file di timbro è determinato dalla variabile `STAMP`, mentre la fine del nome è composta dal nome del task e dal *checksum di input* corrente.

### Nota

Questo schema di denominazione presuppone che `BB_SIGNATURE_HANDLER` è "OEBasicHash", il che è quasi sempre vero nelle versioni attuali di OpenEmbedded.

Per determinare se un task deve essere rieseguito, BitBake verifica se esiste un file di stamp con un checksum di input corrispondente per il task. In tal caso, si presume che l'output del task esista e sia ancora valido. Altrimenti, il task viene rieseguito.

### Nota

Il meccanismo degli stamp [timbratura] è più generale del meccanismo di cache dello shared state (sstate) descritto nella sezione "*I Task Setscene e Shared State*". BitBake evita di rieseguire qualsiasi task che disponga di un file di timbratura valido, non solo i task che possono essere accelerati tramite la cache sstate.

Tuttavia, è importante notare che i file di stamp servono solo come indicatore dell'avvenuta esecuzione di un task e non registrano l'output del task stesso. L'output effettivo del task si trova solitamente in `TMPDIR` (ad esempio, nella `WORKDIR` di alcune ricette). Il meccanismo di cache sstate aggiunge un modo per memorizzare nella cache l'output dei task, che può quindi essere condiviso tra le macchine di compilazione.

Poiché `STAMPS_DIR` è solitamente una sottocartella di `TMPDIR`, la rimozione di `TMPDIR` comporterà anche la rimozione di `STAMPS_DIR`, il che significa che i task verranno rieseguiti correttamente per ripopolare `TMPDIR`.

Se si desidera che un task venga sempre considerata "obsoleta", è possibile contrassegnarla con il "varflag" [flag di variabile] `nostamp`. Se un altro task dipende da tale task, anche quest'ultimo verrà sempre considerato obsoleto, il che potrebbe non essere l'effetto desiderato.

Per informazioni dettagliate su come visualizzare le informazioni sulla firma di un task, consultare la sezione "*Viewing Task Variable Dependencies*" Yocto Project Development Tasks Manual.

## I Task Setscene e Shared State

La descrizione dei task finora presentati presuppone che BitBake debba compilare tutto e che non siano disponibili oggetti precompilati. BitBake supporta la possibilità di saltare i task se sono disponibili oggetti precompilati. Questi oggetti vengono solitamente resi disponibili sotto forma di cache "shared state" (sstate).

### Nota

Per informazioni sulle variabili che influenzano sstate, consultare le variabili `SSTATE_DIR` e `SSTATE_MIRRORS`.

L'idea di un task setscene (ad esempio `do_taskname_setscene`) è una versione del task in cui, invece di compilare qualcosa, BitBake può passare direttamente al risultato finale e posizionare semplicemente un insieme di file in posizioni specifiche a seconda delle necessità. In alcuni casi, ha senso avere una variante del task setscene (ad esempio, la generazione di file di pacchetto nel task `do_package_write_*`). In altri casi, non ha senso (ad esempio, un task `do_patch` o un task `do_unpack`) poiché il lavoro richiesto sarebbe uguale o superiore a quello del task sottostante.

Nel sistema di build, i task comuni che hanno varianti di setscene sono `do_package`, `do_package_write_*`, `do_deploy`, `do_packagedata` e `do_populate_sysroot`. Si noti che questi task rappresentano la maggior parte dei task il cui output è un risultato finale.

Il sistema di build conosce la relazione tra questi task e gli altri task precedenti. Ad esempio, se BitBake esegue `do_populate_sysroot_setscene` per un determinato scopo, non ha senso eseguire nessuna dei task `do_fetch`, `do_unpack`, `do_patch`, `do_configure`, `do_compile` e `do_install` tasks. Tuttavia, se è necessario eseguire `do_package`, BitBake deve eseguire anche questi altri task.

La situazione si complica ulteriormente se tutto può provenire da una cache di stato, perché alcuni oggetti non sono affatto necessari. Ad esempio, non è necessario un compilatore o strumenti nativi, come quilt, se non c'è nulla da compilare o patchare. Se i pacchetti `do_package_write_*` sono disponibili in sstate, BitBake non necessita dei dati del task `do_package`.

Per gestire tutte queste complessità, BitBake viene eseguito in due fasi. La prima è la fase "setscene" [ndt: Prima Fase (Fase di Setscene / Valutazione Cache)]. Durante questa fase, BitBake verifica innanzitutto nella cache di sstate la presenza di eventuali target che intende compilare. BitBake esegue un controllo rapido per verificare se l'oggetto esiste, anziché scaricarlo completamente. Se non viene trovato nulla, la seconda fase, ovvero la fase setscene [ndt: Seconda Fase (Fase di Run / Compilazione Reale)], viene completata e la compilazione principale procede.

Se gli oggetti vengono trovati nella cache di sstate, il sistema di build procede a ritroso a partire dai target finali specificati dall'utente. Ad esempio, se si sta compilando un'immagine, il sistema di compilazione cerca prima i pacchetti necessari per quell'immagine e gli strumenti necessari per crearla. Se questi sono disponibili, il compilatore non è necessario. Pertanto, il compilatore non viene nemmeno scaricato. Se un elemento risulta non disponibile, oppure se il download o il task di impostazione della scena falliscono, il sistema di build tenta di installare le dipendenze, come il compilatore, dalla cache.


La disponibilità degli oggetti nella cache sstate è gestita dalla funzione specificata dalla variabile `BB_HASHCHECK_FUNCTION`, che restituisce un elenco degli oggetti disponibili. La funzione specificata dalla variabile `BB_SETSCENE_DEPVALID` determina se una data dipendenza deve essere rispettata e se, per una data relazione, la funzione deve essere passata. La funzione restituisce un valore True o False.

**Nota**

È possibile firmare questi artefatti con [GPG](#). Per ulteriori informazioni, consultare *Firma dello Stato Condiviso* nel Manuale di Sicurezza di Yocto Project.

**Immagini**

Le immagini prodotte dal sistema di build sono versioni compresse del filesystem root e sono pronte per l'avvio su un dispositivo target. Come si può vedere nella *figura del flusso di lavoro generale*, l'output di BitBake è costituito, in parte, da immagini. Questa sezione esamina più da vicino questo output:

**BitBake****Nota**

Per un elenco di immagini di esempio fornite da Yocto Project, consultare il capitolo *"Immagini"* nel Manuale di Riferimento di Yocto Project.


Il processo di build scrive le immagini nella *Build Directory* all'interno della cartella `tmp/deploy/images/machine/`, come mostrato in figura. Questa cartella contiene tutti i file che si prevede vengano caricati sul dispositivo

di destinazione. La variabile `DEPLOY_DIR` punta alla directory `deploy`, mentre la variabile `DEPLOY_DIR_IMAGE` punta alla directory appropriata contenente le immagini per la configurazione corrente.

- **kernel-image:** Un file binario del kernel. La variabile `KERNEL_IMAGETYPE` determina lo schema di denominazione per il file immagine del kernel. A seconda di questa variabile, il file può iniziare con diverse stringhe di denominazione. La directory `deploy/images/machine` può contenere più file immagine per la macchina.
- **root-filesystem-image:** Filesystem root per il dispositivo target (ad esempio, file `*.ext3` o `*.bz2`). La variabile `IMAGE_FSTYPES` determina il tipo di immagine del filesystem root. La directory `deploy/images/machine` può contenere più filesystem root per la macchina.
- **kernel-modules:** Archivi tar [tarball] contenenti tutti i moduli compilati per il kernel. Gli archivi tar dei moduli del kernel esistono per scopi legacy e possono essere disabilitati impostando la variabile `MODULE_TARBALL_DEPLOY` a "0". La directory `deploy/images/machine` può contenere più archivi tarball di moduli del kernel per la macchina.
- **bootloaders:** Se applicabile alla macchina target, bootloader che supportano l'immagine. La directory `deploy/images/machine` può contenere più bootloader per la macchina.
- **symlinks:** La cartella `deploy/images/machine` contiene un link simbolico che punta al file compilato più di recente per ciascuna macchina. Questi link possono essere utili per script esterni che necessitano di ottenere la versione più recente di ciascun file.

### SDK per lo Sviluppo di Applicazioni

Nella *figura del flusso di lavoro generale*, l'output etichettato "Application Development SDK" rappresenta un SDK. Il processo di generazione dell'SDK varia a seconda che si stia creando un SDK estensibile (ad esempio, `bitbake -c populate_sdk_ext imagedname`) o un SDK standard (ad esempio, `bitbake -c populate_sdk imagedname`). Questa sezione esamina più da vicino questo output:



Nella sua forma specifica, questo output è un insieme di file che include un programma di installazione autoestraente dell'SDK (\*.sh), file manifest per host e target e file utilizzati per il test dell'SDK. Quando si esegue il file di installazione dell'SDK, questo installa l'SDK. L'SDK è composto da una toolchain di sviluppo cross-sviluppo, un insieme di librerie e file di header e uno script di configurazione dell'ambiente SDK. L'esecuzione di questo programma di installazione configura essenzialmente l'ambiente di sviluppo cross-sviluppo. È possibile considerare la toolchain cross-development come la parte "host", poiché viene eseguita sulla macchina SDK. Le librerie e i file di header possono essere considerati come la parte "target", poiché sono compilati per l'hardware target. Lo script di configurazione dell'ambiente viene aggiunto per consentire l'inizializzazione dell'ambiente prima di utilizzare i tool.

#### **i** Nota

- Yocto Project supporta diversi metodi per configurare questo ambiente di sviluppo cross-development. Questi metodi includono il download di programmi di installazione SDK precompilati o la creazione e installazione di un programma di installazione SDK personalizzato.
- Per informazioni di base sulle toolchain cross-development nell'ambiente di sviluppo di Yocto Project, consultare la sezione "*Generazione di Toolchain di Cross-Sviluppo*".
- Per informazioni sulla configurazione di un ambiente di sviluppo cross-development, consultare il manuale *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)*.

Tutti i file di output di un SDK vengono scritti nella cartella `deploy/sdk` all'interno della *Build Directory*, come mostrato nella figura precedente. A seconda del tipo di SDK, esistono diverse variabili per configurare questi file. Le variabili associate a un SDK estensibile sono:

- *DEPLOY\_DIR*: Indica la directory `deploy`.
- *SDK\_EXT\_TYPE*: Controlla se gli artefatti dello "shared state" vengono copiati o meno nell'SDK estensibile. Per default, tutti gli artefatti dello "shared state" richiesti vengono copiati nell'SDK.
- *SDK\_INCLUDE\_PKGDATA*: Specifica se i dati del pacchetto vengono inclusi o meno nell'SDK estensibile per tutte le ricette nel target "world".
- *SDK\_INCLUDE\_TOOLCHAIN*: Specifica se la toolchain viene inclusa o meno durante la compilazione dell'SDK estensibile.
- *ESDK\_LOCALCONF\_ALLOW*: Un elenco di variabili consentite dalla configurazione del sistema di build alla configurazione dell'SDK estensibile.
- *ESDK\_LOCALCONF\_REMOVE*: Elenco di variabili non consentite dalla configurazione del sistema di build alla configurazione dell'SDK estensibile.
- *ESDK\_CLASS\_INHERIT\_DISABLE*: Elenco di classi da rimuovere dal valore *INHERIT* a livello globale all'interno della configurazione dell'SDK estensibile.

Il seguente elenco mostra le variabili associate a un SDK standard:

- *DEPLOY\_DIR*: Indica la directory `deploy`.
- *SDKMACHINE*: Specifica l'architettura della macchina su cui vengono eseguiti gli strumenti di cross-sviluppo per creare i pacchetti per l'hardware target.
- *SDKIMAGE\_FEATURES*: Elenca le funzionalità da includere nella parte "target" dell'SDK.
- *TOOLCHAIN\_HOST\_TASK*: Elenca i pacchetti che costituiscono la parte host dell'SDK (ovvero la parte che viene eseguita su *SDKMACHINE*). Quando si utilizza `bitbake -c populate_sdk imagename` per creare l'SDK, viene applicato un set di pacchetti di default. Questa variabile consente di aggiungere ulteriori pacchetti.
- *TOOLCHAIN\_TARGET\_TASK*: Elenca i pacchetti che compongono la parte target dell'SDK (ovvero la parte compilata per l'hardware di destinazione).
- *SDKPATHINSTALL*: Definisce il path di installazione di default dell'SDK offerto dallo script di installazione.
- *SDK\_HOST\_MANIFEST*: Elenca tutti i pacchetti installati che compongono la parte host dell'SDK. Questa variabile svolge anche un ruolo secondario nello sviluppo di SDK estensibili. Tuttavia, viene utilizzata principalmente per l'SDK standard.
- *SDK\_TARGET\_MANIFEST*: Elenca tutti i pacchetti installati che compongono la parte target dell'SDK. Anche questa variabile svolge un ruolo secondario nello sviluppo di SDK estensibili. Tuttavia, viene utilizzato principalmente per l'SDK standard.


#### 4.3.4 Generazione di Toolchain di Cross-Sviluppo

Yocto Project semplifica notevolmente la creazione delle *The Cross-Development Toolchain*. Questa sezione fornisce alcune informazioni tecniche su come vengono create e utilizzate le toolchain di cross-sviluppo. Per ulteriori informazioni sulle toolchain, è possibile consultare anche il manuale *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)*.



Nell'ambiente di sviluppo di Yocto Project, le toolchain di cross-sviluppo vengono utilizzate per creare immagini e applicazioni che vengono eseguite sull'hardware target. Con pochi comandi, il sistema di build OpenEmbedded crea automaticamente le toolchain necessarie.

La figura seguente mostra un ambiente di build di alto livello per quanto riguarda la creazione e l'utilizzo delle toolchain.



La maggior parte del lavoro viene svolta sull'host di build. Si tratta della macchina utilizzata per creare le immagini e, in generale, per lavorare all'interno dell'ambiente di Yocto Project. Quando si esegue *BitBake* per creare un'immagine, il sistema di build OpenEmbedded utilizza il compilatore `gcc` dell'host per avviare un cross-compilatore chiamato `gcc-cross` (o `clang-cross` se si utilizza Clang). Questo compilatore è quello che BitBake usa per compilare i file sorgente durante la creazione dell'immagine target. Si può pensare a questo compilatore come a un cross-compilatore generato automaticamente e utilizzato internamente solo da BitBake.

La sequenza di eventi che si verifica durante l'avvio della toolchain standard è la seguente:

```
gcc -> virtual/cross-binutils -> linux-libc-headers -> virtual/cross-cc -> libgcc-
->initial -> virtual/libc -> libgcc -> virtual/compilerlibs
```

- `gcc`: Il compilatore, GNU Compiler Collection (GCC), fornito dal *Build Host* o da un tarball di *buildtools*.
- `virtual/cross-binutils`: Le utilità binarie necessarie per eseguire la fase `virtual/cross-cc` dell'operazione di bootstrap e compilare gli header per la libreria C.

- `linux-libc-headers`: File header necessari per il cross-compilatore e la compilazione della libreria C.
- `virtual/cross-cc`: La fase finale del processo di bootstrap per il cross-compilatore. Questa fase genera il cross-compilatore effettivo che BitBake utilizza per creare un'immagine per un dispositivo target.

Questo strumento è "nativo" (ovvero, è progettato per essere eseguito sull'host di compilazione).

- `libgcc-initial`: Una versione iniziale della libreria di supporto GCC necessaria per avviare `virtual/libc`.
- `virtual/libc`: Un provider della libreria standard C (ad esempio, la libreria C GNU).
- `libgcc`: La versione finale della libreria di supporto GCC, che può essere compilata solo se è disponibile una libreria C a cui collegarsi [link].
- `virtual/compilerlibs`: Librerie runtime risultanti dal processo di bootstrapping della toolchain. Questo strumento produce un binario contenente le librerie runtime necessarie per il dispositivo target.

È possibile utilizzare il sistema di build OpenEmbedded per creare un programma di installazione per l'SDK rilocabile utilizzato per sviluppare applicazioni. Quando si esegue il programma di installazione, viene installata la toolchain, che contiene gli strumenti di sviluppo (ad esempio, `gcc-cross-canadian`, `clang-cross-canadian`, `binutils-cross-canadian` e altri strumenti `nativesdk-*`), ovvero strumenti nativi dell'SDK (ovvero nativi di *SDK\_ARCH*), necessari per la cross-compilazione e il test del software. La figura mostra i comandi da utilizzare per creare facilmente questa toolchain. Questa toolchain di sviluppo incrociato è progettata per essere eseguita sulla *SDKMACHINE*, che potrebbe coincidere o meno con la macchina di Build Host.

#### Nota

Se l'architettura target è supportata da Yocto Project, è possibile utilizzare le immagini precompilate fornite con Yocto Project, che contengono già i programmi di installazione della toolchain di cross-sviluppo.

Ecco il processo di bootstrap per la toolchain rilocabile:

```
gcc -> virtual/cross-binutils -> linux-libc-headers -> virtual/cross-cc -> libgcc-
↳initial -> virtual/libc -> gcc-cross-canadian/clang-cross-canadian
```

La catena è identica alla toolchain standard, ad eccezione dell'ultimo elemento: `gcc-cross-canadian` (o `clang-cross-canadian`) è il cross-compilatore rilocabile finale. Quando eseguito sulla *SDKMACHINE*, questo strumento produce codice eseguibile che viene eseguito sul dispositivo target. Viene prodotto un solo compilatore cross-canadian per architettura, poiché è possibile ottimizzarli per diversi processori utilizzando le configurazioni passate al compilatore tramite i comandi di compilazione. Questo evita la necessità di più compilatori e riduce quindi le dimensioni delle toolchain.

#### Nota

L'SDK estensibile non utilizza `gcc-cross-canadian` o `clang-cross-canadian` poiché include una copia del sistema di build OpenEmbedded e la directory di sistema (`sysroot`) al suo interno contiene `gcc-cross`.

**i Nota**

Per informazioni su come utilizzare Clang per l'SDK, consultare [PREFERRED\\_TOOLCHAIN\\_SDK](#).

**i Nota**

Per informazioni sui vantaggi derivanti dalla creazione di un programma di installazione di una toolchain di cross-sviluppo, consultare l'appendice "[Building an SDK Installer](#)" nel Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (eSDK).

### 4.3.5 Cache di Shared State

Per impostazione predefinita, il sistema di build di OpenEmbedded compila tutto da zero, a meno che *BitBake* non riesca a determinare che alcune parti non necessitano di essere ricomilate. Fondamentalmente, la compilazione da zero è vantaggiosa perché significa che tutte le parti vengono compilate da zero e non vi è la possibilità di dati obsoleti che potrebbero causare problemi. Quando gli sviluppatori riscontrano problemi, in genere tornano alla compilazione da zero in modo da avere uno stato noto fin dall'inizio.

La compilazione di un'immagine da zero presenta sia un vantaggio che uno svantaggio. Come accennato nel paragrafo precedente, la compilazione da zero garantisce che tutto sia aggiornato e parta da uno stato noto. Tuttavia, la compilazione da zero richiede anche molto più tempo, poiché generalmente implica la ricompilazione di elementi che non necessariamente necessitano di essere ricompilati.

Yocto Project implementa un codice di "shared state" che supporta le compilazioni incrementali. L'implementazione di questo codice risponde alle seguenti domande, che rappresentavano ostacoli fondamentali per il sistema di supporto alle compilazioni incrementali di OpenEmbedded:

- Quali parti del sistema sono cambiate e quali no?
- Come vengono rimosse e sostituite le parti di software modificate?
- Come vengono utilizzati i componenti precompilati che non necessitano di essere ricostruiti da zero, quando sono disponibili?

Per quanto riguarda la prima domanda, il sistema di compilazione rileva le modifiche agli "input" di un determinato task creando un checksum (o firma) degli input del task stesso. Se il checksum cambia, il sistema presume che gli input siano stati modificati e che il task debba essere rieseguito. Per quanto riguarda la seconda domanda, il codice dello shared state (sstate) tiene traccia di quali task aggiungono quale output al processo di build. Ciò significa che l'output di un determinato task può essere rimosso, aggiornato o altrimenti modificato. La terza domanda trova una risposta parziale nella soluzione per la seconda, presupponendo che il sistema di build possa recuperare gli oggetti sstate da posizioni remote e installarli se ritenuti validi.

**i Nota**

- Il sistema di build non gestisce le informazioni *PR* come parte dei pacchetti di shared state. Di conseguenza, vi sono considerazioni che influiscono sulla gestione dei feed di shared state. Per informazioni su come il sistema di build gestisce i pacchetti e come può tenere traccia dell'incremento delle informazioni *PR*,

consultare la sezione "*Automatically Incrementing a Package Version Number*" nel Manuale di Sviluppo dei Task di Yocto Project.

- Il codice del sistema di build che supporta le build incrementali è complesso. Per le tecniche che consentono di risolvere i problemi relativi al codice dello stato shared, consultare le sezioni "*Viewing Metadata Used to Create the Input Signature of a Shared State Task*" e "*Invalidating Shared State to Force a Task to Run*" entrambe presenti nel Manuale di Sviluppo dei Task di Yocto Project.

Il resto di questa sezione descrive in dettaglio l'architettura generale delle build incrementali, i checksum (firme) e lo shared state.

## Architettura Generale

Quando si determina quali parti del sistema devono essere compilate, BitBake lavora per singolo task anziché per singola ricetta. Ci si potrebbe chiedere perché si preferisca un approccio per singolo task a uno per singola ricetta. Per chiarire, si consideri l'ipotesi di avere il backend di packaging IPK abilitato e poi passare a DEB. In questo caso, gli output dei task `do_install` e `do_package` rimangono validi. Tuttavia, con un approccio per singola ricetta, la build non includerebbe i file `.deb`. Di conseguenza, sarebbe necessario invalidare l'intera build e rieseguirla. Rieseguire tutto non è la soluzione migliore. Inoltre, in questo caso, il core deve essere "istruito" su molti task specifici. Questa metodologia non è scalabile e non consente agli utenti di aggiungere facilmente nuovi task in layer o come ricette esterne senza modificare il "core packaged-staging".

## Checksum (Firme)

Il codice di "shared state" [stato condiviso] utilizza un checksum, ovvero una firma univoca degli input di un task, per determinare se un task deve essere eseguito nuovamente. Poiché è una modifica negli input di un task a innescare la riesecuzione, il processo deve rilevare tutti gli input di un dato task. Per i task di shell, questo risulta piuttosto semplice perché il processo di build genera uno script di shell "run" per ogni task ed è possibile creare un checksum che fornisce una buona indicazione di quando i dati del task cambiano.

A complicare il problema, ci sono elementi che non dovrebbero essere inclusi nel checksum. Innanzitutto, c'è il path di compilazione specifico di un dato task, ovvero la `WORKDIR`. Non importa se la directory di lavoro cambia perché non dovrebbe influire sull'output dei pacchetti target. Inoltre, il processo di compilazione ha l'obiettivo di rendere i pacchetti nativi o cross-rilocabili.

### Nota

Sia i pacchetti nativi che quelli cross-locabili vengono eseguiti sull'host di compilazione. Tuttavia, i pacchetti cross-locabili generano output per l'architettura target.

Il checksum deve quindi escludere `WORKDIR`. L'approccio più semplice per escludere la directory di lavoro consiste nell'impostare `WORKDIR` su un valore fisso e creare il checksum per lo script "run".

Un altro problema deriva dal fatto che gli script "run" contengono funzioni che potrebbero essere chiamate o meno. La soluzione di build incrementale include del codice che individua le dipendenze tra le funzioni di shell. Questo codice viene utilizzato per ridurre gli script "run" al minimo indispensabile, alleviando così questo problema e rendendo gli script "run" molto più leggibili.

Finora, abbiamo trovato soluzioni per gli script di shell. E per i task Python? Si applica lo stesso approccio, anche se questi task sono più complessi. Il processo deve individuare a quali variabili accede una funzione Python e quali funzioni chiama. Anche in questo caso, la soluzione di build incrementale include del codice che prima individua le dipendenze tra variabili e funzioni e poi crea un checksum per i dati utilizzati come input per il task.

Analogamente al caso di *WORKDIR*, possono esserci situazioni in cui le dipendenze devono essere ignorate. In questi casi, è possibile indicare al processo di compilazione di ignorare una dipendenza utilizzando una riga come la seguente:

```
PACKAGE_ARCHS[vardepsexclude] = "MACHINE"
```

Questo esempio garantisce che la variabile *PACKAGE\_ARCHS* non dipenda dal valore di *MACHINE*, anche se lo riferenzia.

Analogamente, ci sono casi in cui è necessario aggiungere dipendenze che BitBake non è in grado di trovare. È possibile farlo utilizzando una riga come la seguente:

```
PACKAGE_ARCHS[vardeps] = "MACHINE"
```

Questo esempio aggiunge esplicitamente la variabile *MACHINE* come dipendenza per *PACKAGE\_ARCHS*.

Ad esempio, si consideri un caso con codice Python inline in cui BitBake non è in grado di individuare le dipendenze. Quando si esegue in modalità debug (ovvero utilizzando `-DDD`), BitBake produce un output quando rileva qualcosa per cui non riesce a individuare le dipendenze. Il team di Yocto Project non è ancora riuscito a trattare in dettaglio queste dipendenze ed è consapevole della necessità di risolvere questa situazione.

Finora, questa sezione si è limitata a discutere gli input diretti di un task. Le informazioni basate sugli input diretti vengono definite "basehash" nel codice. Tuttavia, rimane aperta la questione degli input indiretti di un task, ovvero gli elementi già compilati e presenti nella *Build Directory*. Il checksum (o firma) di un particolare task deve sommare gli hash di tutti i task da cui dipende. La scelta delle dipendenze da aggiungere è una decisione di policy. L'effetto, tuttavia, è quello di generare un checksum che combina il basehash e gli hash delle dipendenze del task.

A livello di codice, esistono diversi modi per influenzare sia il basehash che gli hash dei task dipendenti. Nel file di configurazione di BitBake, è possibile fornire a BitBake alcune informazioni aggiuntive per aiutarlo a costruire il basehash. La seguente istruzione genera di fatto un elenco di variabili globali da escludere dalle dipendenze (ovvero variabili che non vengono mai incluse in alcun checksum):

```
BB_BASEHASH_IGNORE_VARS ?= "TMPDIR FILE PATH PWD BB_TASKHASH BBPATH DL_DIR \\  
    SSTATE_DIR THISDIR FILESEXPATHS FILE_DIRNAME HOME LOGNAME SHELL TERM \\  
    USER FILESPATH STAGING_DIR_HOST STAGING_DIR_TARGET COREBASE PRSERV_HOST \\  
    PRSERV_DUMPDIR PRSERV_DUMPFILE PRSERV_LOCKDOWN PARALLEL_MAKE \\  
    CCACHE_DIR EXTERNAL_TOOLCHAIN CCACHE CCACHE_DISABLE LICENSE_PATH SDKPKGSUFFIX"
```

L'esempio precedente non include *WORKDIR* poiché tale variabile è effettivamente costruita come un path all'interno di *TMPDIR*, che è inclusa nell'esempio precedente.

Le regole per decidere quali hash di task dipendenti includere nelle catene di dipendenza sono più complesse e vengono generalmente implementate tramite una funzione Python. Il codice in `meta/lib/oe/ssstatesig.py` mostra due esempi di questo e illustra anche come è possibile inserire una propria policy nel sistema, se lo si desidera. Questo file definisce i due generatori di firme di base utilizzati da *OpenEmbedded-Core (OE-Core)*: "OEBasic" e

"OEBasicHash". Per default, in BitBake è abilitato un gestore di firme fittizio "noop". Ciò significa che il comportamento è invariato rispetto alle versioni precedenti. OE-Core utilizza per impostazione predefinita il gestore di firme "OEBasicHash" tramite questa impostazione nel file `bitbake.conf`:

```
BB_SIGNATURE_HANDLER ?= "OEBasicHash"
```

Il parametro "OEBasicHash" `BB_SIGNATURE_HANDLER` è identico alla versione "OEBasic" ma aggiunge l'hash del task ai *file stamp*. Questo fa sì che qualsiasi modifica ai metadati che modifichi l'hash del task provochi automaticamente la nuova esecuzione del task stesso. In questo modo si elimina la necessità di incrementare i valori di *PR* e le modifiche ai metadati si propagano automaticamente all'intera build.

È inoltre importante notare che il risultato finale di questi generatori di firme è quello di rendere disponibili al processo di build alcune informazioni sulle dipendenze e sugli hash. Queste informazioni includono:

- `BB_BASEHASH:task-taskname`: Gli hash di base per ogni task nella ricetta.
- `BB_BASEHASH_filename:taskname`: Gli hash di base per ogni task dipendente.
- `BB_TASKHASH`: L'hash del task attualmente in esecuzione.

## Shared State

I checksum e le dipendenze, come discusso nella sezione precedente, risolvono metà del problema del supporto di uno stato condiviso [shared state]. L'altra metà del problema consiste nell'essere in grado di utilizzare le informazioni di checksum durante la compilazione e di riutilizzare o ricompilare componenti specifici.

La classe `sstate` è un'implementazione relativamente generica di come "cattare" un'istantanea di un determinato task. L'idea è che il processo di compilazione non si preoccupi della sorgente dell'output di un task. L'output potrebbe essere appena compilato oppure scaricato ed estratto da qualche altra parte. In altre parole, il processo di compilazione non deve preoccuparsi della sua origine.

Esistono due tipi di output. Un tipo consiste semplicemente nella creazione di una directory in `WORKDIR`. Un buon esempio è l'output di `do_install` o `do_package`. L'altro tipo di output si verifica quando un insieme di dati viene unito in una struttura di directory condivisa [shared] come la sysroot.

Il team di Yocto Project ha cercato di mantenere nascosti i dettagli dell'implementazione nella classe `sstate`. Dal punto di vista dell'utente, aggiungere il wrapping dello "shared state" [stato condiviso] a un task è semplice come nell'esempio `do_deploy` tratto dalla classe `deploy` class:

```
DEPLOYDIR = "${WORKDIR}/deploy-${PN}"
SSTATETASKS += "do_deploy"
do_deploy[sstate-inputdirs] = "${DEPLOYDIR}"
do_deploy[sstate-outputdirs] = "${DEPLOY_DIR_IMAGE}"

python do_deploy_setscene () {
    sstate_setscene (d)
}

addtask do_deploy_setscene
do_deploy[dirs] = "${B}"
```

(continues on next page)

(continua dalla pagina precedente)

```
do_deploy[cleandirs] = "${DEPLOYDIR}"
do_deploy[stamp-extra-info] = "${MACHINE_ARCH}"
```

Il seguente elenco spiega l'esempio precedente:

- Aggiungendo `do_deploy` a `SSTATETASKS` si aggiunge l'elaborazione necessaria relativa allo `sstate`, implementata nella classe `sstate`, prima e dopo il task `do_deploy`.
- La riga `do_deploy[sstate-inputdirs] = "${DEPLOYDIR}"` dichiara che `do_deploy`, quando viene eseguito normalmente (ovvero senza utilizzare la cache `sstate`), posiziona il suo output in `${DEPLOYDIR}`. Questo output diventa l'input per la cache dello `shared state`.
- La riga `do_deploy[sstate-outputdirs] = "${DEPLOY_DIR_IMAGE}"` fa sì che il contenuto della cache dello stato condiviso venga copiato in `${DEPLOY_DIR_IMAGE}`.

#### Nota

Se `do_deploy` non è già presente nella cache di "shared state" [stato condivisa] o se il suo checksum (firma) di input è cambiato rispetto a quando l'output è stato memorizzato nella cache, il task viene eseguito per popolare la cache di `shared state`, dopodiché il contenuto della cache di `shared state` viene copiato in `${DEPLOY_DIR_IMAGE}`. Se `do_deploy` è presente nella cache di `shared state` e la sua firma indica che l'output memorizzato nella cache è ancora valido (ovvero, se nessun input rilevante del task è cambiato), il contenuto della cache di `shared state` viene copiato direttamente in `${DEPLOY_DIR_IMAGE}` dal task `do_deploy_setscene`, saltando il task `do_deploy`.

- La seguente definizione di task rappresenta la logica di collegamento necessaria per rendere effettive le impostazioni precedenti:

```
python do_deploy_setscene () {
    sstate_setscene(d)
}
addtask do_deploy_setscene
```

`sstate_setscene()` accetta i flag sopra indicati come input e, se possibile, accelera il task `do_deploy` attraverso la cache di `shared state`. Se il task è stato accelerato, `sstate_setscene()` restituisce `True`. Altrimenti, restituisce `False` e viene eseguito il normale task `do_deploy`. Per ulteriori informazioni, consultare la sezione "Setscene" nel Manuale Utente di BitBake.

- La riga `do_deploy[dirs] = "${B}"` crea la directory `${B}` prima dell'esecuzione del task `do_deploy` e imposta anche la directory di lavoro corrente di `do_deploy` a `${B}`. (Se la directory esiste già, viene lasciata invariata.) Per ulteriori informazioni, consultare la sezione "Variable Flags" nel Manuale Utente di BitBake.
- La riga `do_deploy[cleandirs] = "${DEPLOYDIR}"` crea la directory vuota `${DEPLOYDIR}` prima dell'esecuzione del task `do_deploy`. (Se la directory esiste già, viene eliminata e ricreata vuota.) Per ulteriori informazioni, consultare la sezione "Variable Flags" nel Manuale Utente di BitBake.

**i Nota**

Nei casi in cui `sstate-inputdirs` e `sstate-outputdirs` coincidano, è possibile utilizzare `sstate-plaindirs`. Ad esempio, per preservare l'output `${PKGDEST}` dal task `do_package`, utilizzare quanto segue:

```
do_package[sstate-plaindirs] = "${PKGDEST}"
```

- La riga `do_deploy[stamp-extra-info] = "${MACHINE_ARCH}"` aggiunge metadati extra al file *stamp file*. In questo caso, i metadati rendono il task specifico per l'architettura di una macchina. Consultare la sezione "The Task List" nel Manuale Utente di BitBake per ulteriori informazioni sul flag `stamp-extra-info`.
- `sstate-inputdirs` e `sstate-outputdirs` possono essere utilizzati anche con più directory. Ad esempio, il seguente codice dichiara `PKGDESTWORK` e `SHLIBWORK` come directory di input dello stato condiviso, che popolano la cache dello stato condiviso, e `PKGDATA_DIR` e `SHLIBSDIR` come corrispondenti directory di output dello stato condiviso [shared state]:

```
do_package[sstate-inputdirs] = "${PKGDESTWORK} ${SHLIBWORKDIR}"
do_package[sstate-outputdirs] = "${PKGDATA_DIR} ${SHLIBSDIR}"
```

- Questi metodi includono anche la possibilità di utilizzare un file di blocco durante la manipolazione delle strutture delle directory dello stato condiviso, per i casi in cui l'aggiunta o la rimozione di file è un'operazione delicata:

```
do_package[sstate-lockfile] = "${PACKAGELOCK}"
```

Dietro le quinte, il codice dello stato condiviso funziona cercando i file di stato condiviso in `SSTATE_DIR` e `SSTATE_MIRRORS`. Ecco un esempio:

```
SSTATE_MIRRORS ?= "\
file:///.* https://someserver.tld/share/sstate/PATH;downloadfilename=PATH \
file:///.* file:///some/local/dir/sstate/PATH"
```

**i Nota**

La directory dello stato condiviso [shared state] (`SSTATE_DIR`) è organizzata in sottodirectory di due caratteri, i cui nomi si basano sui primi due caratteri dell'hash. Se la struttura della directory di stato condiviso per un mirror ha la stessa struttura di `SSTATE_DIR`, è necessario specificare "PATH" come parte dell'URI per consentire al sistema di compilazione di mappare la sottodirectory appropriata.

La validità del pacchetto di stato condiviso può essere rilevata semplicemente esaminando il nome del file, poiché quest'ultimo contiene il checksum (o la firma) del task, come descritto in precedenza in questa sezione. Se viene trovato un pacchetto di stato condiviso valido, il processo di compilazione lo scarica e lo utilizza per accelerare il task.



I processi di compilazione utilizzano i task `*_setscene` per la fase di accelerazione dei task. BitBake esegue questa fase prima del codice di esecuzione principale e tenta di accelerare tutte i task per i quali riesce a trovare pacchetti di stato condiviso. Se è disponibile un pacchetto di stato condiviso per un task, questo viene utilizzato. Ciò significa che il task e tutti i task da cui dipende non vengono eseguiti.

Come esempio concreto, l'obiettivo è che, durante la creazione di un'immagine basata su IPK, solo i task `do_package_write_ipk` abbiano i loro pacchetti di stato condivisi scaricati ed estratti. Poiché il sysroot non viene utilizzato, non verrà mai estratto. Questo è un altro motivo per cui un approccio basato sui task è preferibile a un approccio basato sulle ricette, che dovrebbe installare l'output di ogni singolo task.

## Equivalenza degli Hash

La sezione precedente ha spiegato come BitBake salta l'esecuzione dei task il cui output è già presente nella cache dello stato condiviso.

Durante una build, può capitare che l'output/risultato di un task rimanga invariato nonostante le modifiche ai valori di input del task stesso. Un esempio potrebbe essere la modifica degli spazi bianchi in del codice C di input. In termini di progetto, questo è ciò che definiamo "equivalenza".

Per tenere traccia di tale equivalenza, BitBake deve gestire tre hash per ogni task:

- I *task hash*, spiegato in precedenza: calcolato a partire dai metadati della ricetta, dal codice del task e dai valori hash delle sue dipendenze. Quando vengono apportate modifiche, questi hash vengono quindi modificati, causando la riesecuzione del task. Di conseguenza, vengono modificati anche gli hash dei task che dipendono da questo task, causando la riesecuzione dell'intera catena di dipendenze.
- L'*output hash*, un nuovo hash calcolato a partire dall'output dei task dello Shared State, ovvero i task che salvano il loro output risultante in un file tarball dello Shared State. La mappatura tra l'hash del task e il suo hash di output viene segnalata a un nuovo server di *Hash Equivalence*. Questa mappatura viene memorizzata in un database dal server per riferimenti futuri.
- L'*unihash*, un nuovo hash, viene inizialmente impostato sull'hash del task. Questo viene utilizzato per tracciare l'*unicità* dell'output del task e spiegheremo come viene mantenuto il suo valore.

Quando l'Hash Equivalence è abilitata, BitBake calcola l'hash di ciascun task utilizzando l'unihash delle sue dipendenze, anziché il loro hash.

Ora, immaginiamo che un task di Shared State venga modificata a causa di una modifica al suo codice o ai suoi metadati, oppure a causa di una modifica alle sue dipendenze. Poiché ciò modifica il suo hash, il task dovrà essere rieseguito. Il suo hash di output verrà quindi ricalcolato.

Successivamente, la nuova mappatura tra il nuovo hash del task e il suo hash di output verrà segnalata al server di Hash Equivalence. Il server comunicherà a BitBake se l'hash di output corrisponde a un hash di output precedentemente segnalato, relativo a un hash di task diverso.

Se l'hash di output è già noto, BitBake aggiornerà l'unihash del task in modo che corrisponda all'hash del task originale che ha generato quell'output. In questo modo, i task dipendenti manterranno l'hash precedentemente registrato e BitBake sarà in grado di recuperare il loro output dalla cache dello Shared State, anziché rieseguirle. Analogamente, anche l'output dei task successive può essere recuperato dallo Shared State.

Se l'hash di output non è noto, verrà creata una nuova voce sul server di Hash Equivalence, associando l'hash del task a quell'output. I task dipendenti, che avranno ancora un nuovo hash a causa della modifica, dovranno essere rieseguiti come previsto. La modifica si propaga ai task dipendenti.

In sintesi, quando l'Hash Equivalence è abilitata, una modifica in una dei task nella coda di esecuzione di BitBake non deve necessariamente propagarsi a tutti i task a valle che dipendono dall'output di tale task, causando una ricostruzione completa di questi task, e così via con i task dipendenti successive. Invece, quando l'output di questi task rimane identico all'output registrato in precedenza, BitBake può recuperare in modo sicuro l'output di tutti i task a valle dalla cache dello Shared State.

#### Nota

Avere *Reproducible Builds* è un ingrediente fondamentale per la stabilità dell'hash di output di un task. Pertanto, l'efficacia dell'Hash Equivalence dipende fortemente da essa.

Le ricette non riproducibili potrebbero presentare comportamenti indesiderati se l'hash equivalence è abilitata, poiché l'output divergente non riproducibile potrebbe essere rimappato dal server a un oggetto sstate precedente nella cache. Se una ricetta non è riproducibile per motivi banali, come timestamp diversi, questo probabilmente non rappresenta un problema. Tuttavia, le ricette che presentano modifiche più drastiche (come nomi di file completamente diversi) probabilmente falliranno del tutto, poiché gli oggetti sstate a valle non sono effettivamente equivalenti a quelli appena creati.

Questo si applica a diversi scenari:

- Una modifica "banale" a una ricetta che non influisce sull'output generato, come ad esempio modifiche agli spazi bianchi, ai path di codice non utilizzati o all'ordine delle variabili.
- Aggiornamenti di librerie shared [condivise], ad esempio per correggere una vulnerabilità di sicurezza. Certamente, i programmi che utilizzano tale libreria dovrebbero essere ricompilati, ma i loro nuovi binari dovrebbero rimanere identici. Le attività corrispondenti dovrebbero avere un hash di output diverso a causa della modifica dell'hash della loro dipendenza dalla libreria, ma grazie al fatto che il loro output è identico, l'equivalenza dell'hash bloccherà la propagazione lungo la catena di dipendenza.
- Aggiornamenti di strumenti nativi. Sebbene i task dipendenti debbano essere ricompilati, è probabile che generino lo stesso output e vengano contrassegnati come equivalenti.

Questo meccanismo è abilitato di default in Poky ed è controllato da tre variabili:

- `BB_HASHSERVE`, che specifica un server di equivalenza dell'hash locale o remoto da utilizzare.
- `BB_HASHSERVE_UPSTREAM`, quando `BB_HASHSERVE = "auto"`, consente di connettere il server locale a un server upstream.
- `BB_SIGNATURE_HANDLER`, che deve essere impostato su `OEEquivHash`.

Pertanto, la configurazione di default in Poky corrisponde alle seguenti impostazioni:

```
BB_HASHSERVE = "auto"
BB_SIGNATURE_HANDLER = "OEEquivHash"
```

In alternativa all'avvio di un server locale, è possibile utilizzare un server di equivalenza hash in rete, impostando:

```
BB_HASHSERVE = "<HOSTNAME>:<PORT>"
```

La configurazione di un server di equivalenza hash è descritta nella sezione *Setting up a Hash Equivalence Server* del Manuale di Sviluppo dei Task di Yocto Project.

Guardare il [video](#) della presentazione di Joshua Watt su *Hash Equivalence and Reproducible Builds* all'ELC 2020 per un'introduzione molto sintetica all'implementazione dell'equivalenza hash in Yocto Project.

### 4.3.6 Dipendenze di Runtime Aggiunte Automaticamente

Il sistema di build OpenEmbedded aggiunge automaticamente i tipi più comuni di dipendenze di runtime tra i pacchetti, il che significa che non è necessario dichiarare esplicitamente i pacchetti utilizzando *RDEPENDS*. Esistono tre meccanismi automatici (*shlibdeps*, *pcdeps* e *depchains*) che gestiscono rispettivamente le librerie shared, i moduli di configurazione dei pacchetti (*pkg-config*) e i pacchetti *-dev* e *-dbg*. Per altri tipi di dipendenze di runtime, è necessario dichiararle manualmente.

- *shlibdeps*: Durante il task *do\_package* di ogni ricetta, vengono individuate tutte le librerie shared installate dalla ricetta. Per ogni libreria shared, il pacchetto che la contiene viene registrato come fornitore della libreria stessa. Più specificamente, il pacchetto viene registrato come fornitore del *soname* della libreria. La mappatura risultante tra shared condivise e pacchetti viene salvata a livello globale in *PKGDATA\_DIR* dal task *do\_packagedata*.

Contemporaneamente, tutti gli eseguibili e le librerie shared installati dalla ricetta vengono esaminati per verificare a quali librerie shared si collegano. Per ogni dipendenza da libreria shared trovata, viene interrogata *PKGDATA\_DIR* per verificare se qualche pacchetto (probabilmente di una ricetta diversa) contiene la libreria shared. Se viene trovato un pacchetto di questo tipo, viene aggiunta una dipendenza di runtime dal pacchetto che dipende dalla libreria shared al pacchetto che contiene la libreria.

La dipendenza di runtime aggiunta automaticamente include anche una restrizione di versione. Questa restrizione di versione specifica che deve essere utilizzata almeno la versione corrente del pacchetto che fornisce la libreria shared, come se "package (>= version)" fosse stato aggiunto a *RDEPENDS*. Questo impone l'aggiornamento del pacchetto contenente la libreria shared durante l'installazione del pacchetto che dipende da tale libreria, se necessario.

Per evitare che un pacchetto venga registrato come fornitore di una particolare libreria shared (ad esempio, perché la libreria è destinata esclusivamente all'uso interno), è necessario aggiungere la libreria a *PRIVATE\_LIBS* all'interno della ricetta del pacchetto.

- *pcdeps*: Durante il task *do\_package* di ogni ricetta, vengono individuati tutti i moduli *pkg-config* (file *file``\*.pc``*) installati dalla ricetta. Per ogni modulo, il pacchetto che lo contiene viene registrato come fornitore del modulo. La mappatura modulo-pacchetto risultante viene salvata globalmente in *PKGDATA\_DIR* dal task *do\_packagedata*.

Contemporaneamente, tutti i moduli *pkg-config* installati dalla ricetta vengono esaminati per verificare da quali altri moduli *pkg-config* dipendono. Un modulo viene considerato dipendente da un altro modulo se contiene una riga "Requires:" che specifica l'altro modulo. Per ogni dipendenza tra moduli, viene interrogata la directory *PKGDATA\_DIR* per verificare se qualche pacchetto contiene il modulo. Se viene trovato un pacchetto di questo tipo, viene aggiunta una dipendenza di runtime dal pacchetto che dipende dal modulo al pacchetto che lo contiene.

**i Nota**

Il meccanismo `pcdeps` deduce più spesso le dipendenze tra pacchetti con l'opzione `-dev`.

- `depchains`: Se un pacchetto `foo` dipende da un pacchetto `bar`, allora anche `foo-dev` e `foo-dbg` diventano dipendenti rispettivamente da `bar-dev` e `bar-dbg`. Prendendo come esempio i pacchetti `-dev`, il pacchetto `bar-dev` potrebbe fornire i file header e i link simbolici alle librerie `shared` necessari a `foo-dev`, il che dimostra la necessità di una dipendenza tra i pacchetti. Le dipendenze aggiunte da, il che dimostra la necessità di una dipendenza tra i pacchetti.

Le dipendenze aggiunte da `depchains` sono nella forma di *RRECOMMENDS*.

**i Nota**

Per default, `foo-dev` ha anche una dipendenza di tipo *RDEPENDS* da `foo`, poiché il valore di default di `RDEPENDS:${PN}-dev` (impostato in `bitbake.conf`) include `"${PN}"`.

Per garantire che la catena di dipendenze non venga mai interrotta, i pacchetti `-dev` e `-dbg` vengono sempre generati per default, anche se risultano vuoti. Per ulteriori informazioni, consultare la variabile *ALLOW\_EMPTY*.

Il task *do\_package* dipende dal task *do\_packagedata* di ogni ricetta in *DEPENDS* tramite l'uso di una dichiarazione `[deptask]`, che garantisce che le informazioni di mappatura tra libreria condivisa/modulo e pacchetto richieste saranno disponibili quando necessario, purché *DEPENDS* sia stato impostato correttamente.

### 4.3.7 Fakeroot e Pseudo

Alcuni task sono più facili da implementare quando è consentito loro di eseguire determinate operazioni normalmente riservate all'utente `root` (ad esempio *do\_install*, *do\_package\_write\**, *do\_rootfs* e *do\_image\**). Ad esempio il task *do\_install* trae vantaggio dalla possibilità di impostare l'UID e il GID dei file installati su valori arbitrari.

Un approccio per consentire ai task di eseguire operazioni riservate all'utente `root` sarebbe quello di richiedere l'esecuzione di *BitBake* come `root`. Tuttavia, questo metodo è macchinoso e presenta problemi di sicurezza. L'approccio effettivamente utilizzato consiste nell'eseguire i task che beneficiano dei privilegi di `root` in un ambiente `root` "fittizio". In questo ambiente, il task e i suoi processi figli credono di essere in esecuzione come utente `root` e vedono una visione internamente coerente del filesystem. Finché la generazione dell'output finale (ad esempio un pacchetto o un'immagine) non richiede privilegi di `root`, il fatto che alcuni passaggi precedenti siano stati eseguiti in un ambiente `root` fittizio non causa problemi.

La capacità di eseguire task in un ambiente `root` fittizio è nota come "*fakeroot*", che deriva dalla parola chiave/variabile flag di *BitBake* che richiede un ambiente `root` fittizio per un task.

Nel *OpenEmbedded Build System*, il programma che implementa *fakeroot* è noto come *Pseudo*. *Pseudo* sovrascrive le chiamate di sistema utilizzando la variabile d'ambiente `LD_PRELOAD`, creando l'illusione di essere in esecuzione come `root`. Per tenere traccia della proprietà e dei permessi "fittizi" dei file risultanti da operazioni che richiedono i permessi di `root`, *Pseudo* utilizza un database *SQLite 3*. Questo database è memorizzato in `${WORKDIR}/pseudo/files.db` per ogni singola ricetta. La memorizzazione del database in un file anziché in memoria garantisce la persistenza tra le attività e le build, cosa che non si ottiene con *fakeroot*.

**i Nota**

Se si aggiunge un proprio task che manipola gli stessi file o directory di un task fakeroot, anche tale task deve essere eseguito con i permessi di root. In caso contrario, il task non può eseguire operazioni che richiedono solo i permessi di root e non può visualizzare la proprietà e i permessi fittizi dei file impostati dall'altro task. È inoltre necessario aggiungere una dipendenza da `virtual/fakeroot-native:do_populate_sysroot`, specificando quanto segue:

```
fakeroot do_mytask () {
    ...
}
do_mytask[depends] += "virtual/fakeroot-native:do_populate_sysroot"
```

Per ulteriori informazioni, consultare le variabili **FAKEROOT\*** nel Manuale Utente di BitBake. Per ulteriori informazioni su Fakeroot e Pseudo, si può anche consultare l'articolo "[Why Not Fakeroot?](#)".

### 4.3.8 Mappa dei Task di BitBake

Per comprendere il funzionamento di BitBake nella directory e nell'ambiente di build, possiamo considerare le seguenti ricette e il diagramma, per avere un quadro completo dei task che BitBake esegue per generare il file di pacchetto finale per la ricetta.

Prenderemo due ricette come esempio:

- `libhello`: Una ricetta che fornisce una libreria shared
- `sayhello`: Una ricetta che utilizza la libreria `libhello` per svolgere il suo compito

**i Nota**

`sayhello` dipende da `libhello` in fase di compilazione, poiché necessita della libreria shared per eseguire il processo di link dinamico. Dipende da essa anche in fase di esecuzione, poiché il loader di librerie shared deve trovare la libreria. Per maggiori dettagli sulle dipendenze, consultare [Dependencies](#).

I sorgenti di `libhello` sono i seguenti:

- `LICENSE`: Questa è la licenza associata a questa libreria
- `Makefile`: Il file utilizzato da `make` per compilare la libreria
- `hellolib.c`: L'implementazione della libreria
- `hellolib.h`: Il file header C della libreria

I sorgenti di `sayhello` sono i seguenti:

- `LICENSE`: Questa è la licenza associata a questo progetto
- `Makefile`: Il file utilizzato da `make` per compilare il progetto
- `sayhello.c`: Il file sorgente del progetto

Prima di presentare il contenuto di ciascun file, ecco i passaggi da seguire per raggiungere il nostro obiettivo, ovvero integrare `sayhello` nel nostro file system principale:

1. Creare un repository Git per ogni progetto con i file corrispondenti
2. Creare una ricetta per ogni progetto
3. Assicurarsi che la ricetta `sayhello` *DEPENDS* da `libhello`
4. Assicurarsi che la ricetta `sayhello` *RDEPENDS* da `libhello`
5. Aggiungere `sayhello` a *IMAGE\_INSTALL* per integrarlo nel file system di root

Il contenuto di `libhello/Makefile` è il seguente:

```
LIB=libhello.so

all: $(LIB)

$(LIB): hellolib.o
    $(CC) $< -Wl,-soname,$(LIB).1 -fPIC $(LDFLAGS) -shared -o $(LIB).1.0

%.o: %.c
    $(CC) -c $<

clean:
    rm -rf *.o *.so*
```

### Nota

Quando si creano librerie shared, si raccomanda vivamente di seguire le convenzioni e le linee guida di Linux (vedere [questo articolo](#) per maggiori informazioni).

### Nota

Quando si creano file `Makefile`, i raccomanda vivamente di utilizzare `CC`, `LDFLAGS` e `CFLAGS` poiché BitBake li imposterà come variabili d'ambiente in base alla configurazione di compilazione.

Il contenuto di `libhello/hellolib.h` è il seguente:

```
#ifndef HELLOLIB_H
#define HELLOLIB_H

void Hello();

#endif
```

Il contenuto di `libhello/hellolib.c` è il seguente:

```
#include <stdio.h>

void Hello(){
    puts("Hello from a Yocto demo \n");
}
```

Il contenuto di sayhello/Makefile è:

```
EXEC=sayhello
LDFLAGS += -lhello

all: $(EXEC)

$(EXEC): sayhello.c
    $(CC) $< $(LDFLAGS) $(CFLAGS) -o $(EXEC)

clean:
    rm -rf $(EXEC) *.o
```

Il contenuto di sayhello/sayhello.c è il seguente:

```
#include <hellolib.h>

int main(){
    Hello();
    return 0;
}
```

Il contenuto di libhello\_0.1.bb è il seguente:

```
SUMMARY = "Hello demo library"
DESCRIPTION = "Hello shared library used in Yocto demo"

# NOTE: Set the License according to the LICENSE file of your project
#       and then add LIC_FILES_CHKSUM accordingly
LICENSE = "CLOSED"

# Assuming the branch is main
# Change <username> accordingly
SRC_URI = "git://github.com/<username>/libhello;branch=main;protocol=https"

do_install(){
    install -d ${D}${includedir}
    install -d ${D}${libdir}
```

(continues on next page)

(continua dalla pagina precedente)

```

install hellolib.h ${D}${includedir}
oe_soinstall ${PN}.so.${PV} ${D}${libdir}
}

```

Il contenuto di `sayhello_0.1.bb` è il seguente:

```

SUMMARY = "SayHello demo"
DESCRIPTION = "SayHello project used in Yocto demo"

# NOTE: Set the License according to the LICENSE file of your project
#       and then add LIC_FILES_CHKSUM accordingly
LICENSE = "CLOSED"

# Assuming the branch is main
# Change <username> accordingly
SRC_URI = "git://github.com/<username>/sayhello;branch=main;protocol=https"


DEPENDS += "libhello"
RDEPENDS:${PN} += "libhello"

do_install() {
    install -d ${D}${bindir}
    install -m 0700 sayhello ${D}${bindir}
}

```

Dopo aver inserito le ricette in un layer personalizzato, possiamo eseguire `bitbake sayhello` per compilare la ricetta.

Il diagramma seguente mostra la sequenza di operazioni che BitBake esegue per raggiungere questo obiettivo.



Poiché questo manuale presenta informazioni su molti argomenti diversi, si consiglia di consultare materiale supplementare per una comprensione completa. Per ulteriori informazioni introduttive sul Yocto Project, consultare il sito web di Yocto Project all'indirizzo del [Sito Web di Yocto Project](#). Per creare un'immagine senza alcuna conoscenza di Yocto Project per testarlo rapidamente, consultare il documento *Build Rapida di un'Immagine con lo Yocto Project*. Per un elenco completo di link e altra documentazione, consultare la sezione *"Links and Related Documentation"* nel Manuale di Riferimento di Yocto Project.



The Yocto Project ®

[<docs@lists.yoctoproject.org>](mailto:docs@lists.yoctoproject.org)

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.



---

## Guida per i Collaboratori di Yocto Project e di OpenEmbedded

---

Yocto Project e OpenEmbedded sono progetti open-source basati sulla community, quindi i contributi sono benvenuti: è così che il codice si evolve e chiunque può apportare modifiche. I contributi possono assumere diverse forme: se si ha una soluzione per un problema riscontrato, una patch è il modo più appropriato per contribuire. Se si riscontra un problema ma non si ha una soluzione, segnalare un difetto in [Bugzilla](#) o porre domande sulle mailing list potrebbe essere più appropriato. Questa guida ha lo scopo di indicare la giusta direzione.

### 5.1 Identificazione del Componente

L'ecosistema Yocto Project e OpenEmbedded è costituito da *layer*, quindi il primo passo è identificare il componente in cui è più probabile che risieda il problema. Ad esempio, se si riscontra un problema hardware, è probabile che sia correlato al BSP in uso e il posto migliore a cui rivolgersi per chiedere consiglio è il fornitore del BSP o il *layer*. Se il problema riguarda la compilazione/configurazione e si utilizza una distribuzione, quest'ultima sarà probabilmente il primo punto di riferimento. Se il problema è generico e/o riguarda le classi principali o i metadati, il componente appropriato potrebbe essere il core layer o BitBake.

Ogni layer di metadati utilizzato dovrebbe contenere un file `README` che spiega dove segnalare i problemi, dove inviare le modifiche e come contattare i manutentori.

Se il problema si trova nel livello dei metadati principali (OpenEmbedded-Core) o in BitBake, è possibile segnalarlo nel [Yocto Project Bugzilla](#). La mailing list [yocto](#) è un punto di riferimento generico dove è possibile inviare domande se non si riesce a capire dove indirizzarle.

### 5.2 Segnalazione di un Difetto in Yocto Project e in OpenEmbedded

È possibile utilizzare l'istanza di [Bugzilla](#) di Yocto Project per segnalare un difetto (bug) relativo a BitBake, OpenEmbedded-Core, qualsiasi altro componente di Yocto Project o per problemi con gli strumenti. Per ulteriori informazioni su questa implementazione di Bugzilla, consultare la sezione "[Yocto Project Bugzilla](#)" nel Manuale di

Riferimento di Yocto Project. Per maggiori dettagli su ciascuno dei seguenti passaggi, consultare la pagina wiki di Bugzilla di Yocto Project [Bugzilla wiki page](#).

Seguire i seguenti passaggi generali per segnalare un bug:

1. Aprire l'implementazioni di Yocto Project di [Bugzilla](#).
2. Cliccare su "File a Bug" per inserire un nuovo bug.
3. Scegliere "Classification", "Product" e "Component" appropriati per i quali è stato riscontrato il bug. I bug di Yocto Project rientrano in diverse classificazioni, che a loro volta si suddividono in vari prodotti e componenti. Ad esempio, per un bug relativo al layer `meta-intel`, si dovrebbe scegliere rispettivamente "Build System, Metadata & Runtime", "BSPs" e "bsps-meta-intel".
4. Scegliere la "Version" di Yocto Project per cui si è riscontrato il bug (ad esempio, 6.1).
5. Determinare e selezionare la "Severity" del bug. La severity [gravità] indica l'impatto del bug sul lavoro.
6. Scegliere l'"Hardware" interessato dal bug.
7. Scegliere l'"Architecture" interessata dal bug.
8. Selezionare "Documentation change" per il bug. La correzione di un bug potrebbe avere o meno un impatto sulla documentazione di Yocto Project. Se non si è certi dell'impatto sulla documentazione, selezionare "Don't Know".
9. Fornire un breve "Summary" [riepilogo] del bug. Cercare di limitarlo a una o due righe e assicurarsi di cogliere l'essenza del bug.
10. Fornire una "Description" dettagliata del bug. Si deve fornire il maggior numero possibile di dettagli sul contesto, il comportamento, l'output e così via relativi al bug. Si possono anche allegare file di supporto, come ad esempio i log, utilizzando il pulsante "Add an attachment".
11. Cliccare sul pulsante "Submit Bug" per inviare il bug. Al bug verrà assegnato un nuovo numero Bugzilla e il difetto verrà registrato nel sistema di tracciamento dei bug.

Una volta segnalato un bug, questo verrà elaborato dallo Yocto Project Bug Triage Team, che assegnerà ulteriori dettagli (ad esempio, priorità e responsabile). Voi siete gli autori della segnalazione del bug e qualsiasi ulteriore categorizzazione, progresso o commento sul bug comporterà l'invio automatico di un'email da parte di Bugzilla in merito alla specifica modifica o allo stato di avanzamento della risoluzione del bug.

Non vi è alcuna garanzia che un bug venga risolto o meno, poiché un progetto open source non dispone di risorse di sviluppo dedicate. Tuttavia, il progetto ha una buona reputazione per quanto riguarda la risoluzione dei problemi comuni a medio e lungo termine. Incoraggiamo gli utenti a segnalare i bug in modo che i problemi siano almeno noti. Questo aiuta gli altri utenti quando trovano qualcuno che ha riscontrato lo stesso problema, e un problema sconosciuto ha molte meno probabilità di essere risolto!

## 5.3 Guida di Stile per le Ricette

### 5.3.1 Convenzioni di Nomenclatura delle Ricette

In generale, la maggior parte delle ricette dovrebbe seguire la convenzione di denominazione `recipes-category/recipe-name/recipe-name_version.bb`. Le ricette per progetti correlati possono condividere la stessa directory.

`recipeName` e `category` possono contenere trattini, ma i trattini non sono consentiti in `version`.

Se la ricetta fa riferimento a una revisione Git che non corrisponde a una versione rilasciata del software, `version` può essere `git` (ad esempio, `recipeName_git.bb`) e la ricetta imposterà `PV`.

### 5.3.2 Politica sulle Versioni

Le nostre versioni seguono il formato `<epoch>:<version>-<revision>` o, in termini di variabili BitBake, `_${PE}:${PV}-${PR}`. Generalmente seguiamo la politica sulle versioni di [Debian](#) che definisce questi termini.

Nella maggior parte dei casi, la versione `PV` verrà impostata automaticamente dal nome del file della ricetta. Si consiglia di utilizzare le versioni rilasciate del software, poiché si tratta delle revisioni che gli sviluppatori si aspettano vengano utilizzate.

Le versioni delle ricette dovrebbero sempre essere confrontate e ordinate correttamente in modo che gli aggiornamenti funzionino come previsto. Con le versioni convenzionali come `1.4` che vengono aggiornate a `1.5`, questo avviene naturalmente, ma alcune versioni non vengono ordinate correttamente. Ad esempio, `1.5 Release Candidate 2` potrebbe essere scritto come `1.5rc2` ma questo ordine viene eseguito dopo `1.5`, quindi gli aggiornamenti dai feed non avverranno correttamente.

In alternativa, è possibile utilizzare l'operatore tilde (`~`), che ordina prima della stringa vuota, quindi `1.5~rc2` viene prima di `1.5`. Esiste una sintassi storica in cui `PV` viene impostato come una combinazione della versione precedente + della versione di pre-release, ad esempio `PV=1.4+1.5rc2`. Questa sintassi è valida, ma la forma con la tilde è preferibile.

Per i confronti tra versioni, il programma `opkg-compare-versions` di `opkg-utils` può essere utile per determinare come si confrontano due numeri di versione. Il nostro algoritmo definitivo per il confronto delle versioni è quello integrato in bitbake, che mira a essere il più possibile simile a quelli dei gestori di pacchetti e alle politiche di Debian.

Quando una ricetta fa riferimento a una revisione Git che non corrisponde a una versione rilasciata del software (ad esempio, non è una versione con tag), la variabile `PV` deve includere il segno `+`, in modo che `bitbake` includa automaticamente le informazioni sulla versione del pacchetto durante la fase di creazione del pacchetto.

```
PV = "<version>+git"
```

In questo caso, `<version>` dovrebbe essere la versione più recente del software rilasciata a partire dalla revisione corrente del codice sorgente (`git describe` può essere utile per determinarla). Sebbene non sia consigliato per i layer pubblicati, questo formato è utile anche quando si utilizza `AUTOREV` per impostare la ricetta in modo che incrementi automaticamente le revisioni del controllo di versione, il che può essere utile durante lo sviluppo locale.

### 5.3.3 Modifiche al Numero di Versione

La variabile `PR` viene utilizzata per indicare le diverse revisioni di una ricetta che fanno riferimento alla stessa versione del sorgente upstream. Può essere utilizzata per forzare l'installazione di una nuova versione di una ricetta su un dispositivo da un feed di pacchetti. In passato, queste variabili dovevano essere impostate manualmente, ma nella maggior parte dei casi ora possono essere impostate e incrementate automaticamente da un PR Server connesso a un feed di pacchetti.

Quando `PV` aumenta, qualsiasi valore `PR` esistente può e deve essere rimosso.

Se *PV* cambia in modo tale da non aumentare rispetto al valore precedente, è necessario incrementare *PE* per garantire che i gestori di pacchetti lo aggiornino correttamente. Se non è impostato, è consigliabile impostare *PE* a "1" poiché il valore predefinito vuoto può essere facilmente confuso con "0" a seconda del gestore di pacchetti. *PE* può assumere solo un valore intero.

## 5.3.4 Formattazione delle Ricette

### Formattazione delle Variabili

- L'assegnazione di una variabile deve includere uno spazio attorno all'operatore, ad esempio `FOO = "bar"`, non `FOO="bar"`.
- Le virgolette doppie devono essere utilizzate a destra dell'assegnazione, ad esempio `FOO = "bar"` non `FOO = 'bar'`
- Gli spazi devono essere utilizzati per l'indentazione delle variabili, con 4 spazi per tabulazione.
- Le variabili long devono essere suddivise su più righe, quando possibile, utilizzando il carattere di continuazione (`\`)
- Quando si suddivide una variabile lunga su più righe, tutte le righe di continuazione devono essere rientrate (con spazi) per allinearsi all'inizio della virgoletta sulla prima riga:

```
FOO = "this line is \  
      long \  
      "
```

Invece di:

```
FOO = "this line is \  
long \  
"
```

### Formattazione delle Funzioni Python

- Gli spazi devono essere utilizzati per l'indentazione del codice Python, con 4 spazi per tabulazione.

### Formattazione delle Funzioni Shell

- La formattazione delle funzioni shell deve essere coerente all'interno dei layer. Alcune utilizzano le tabulazioni, altre gli spazi.

## 5.3.5 Metadati della ricetta

### Variabili Obbligatorie

Le seguenti variabili devono essere incluse in tutte le ricette:

- *SUMMARY*: una descrizione di una riga del progetto upstream.
- *DESCRIPTION*: una descrizione estesa del progetto upstream, eventualmente su più righe. Se non è possibile scrivere una descrizione adeguata, questa può essere omessa poiché il valore di default è *SUMMARY*.

- *HOMEPAGE*: l'URL della homepage del progetto upstream.
- *BUGTRACKER*: l'URL del sito web di tracciamento dei bug del progetto upstream, se applicabile.

### Ordinamento delle Ricette

Quando una variabile viene definita in ricette e classi, le variabili dovrebbero seguire, ove possibile, il seguente ordine generale:

- *SUMMARY*
- *DESCRIPTION*
- *HOMEPAGE*
- *BUGTRACKER*
- *SECTION*
- *LICENSE*
- *LIC\_FILES\_CHKSUM*
- *DEPENDS*
- *PROVIDES*
- *PV*
- *SRC\_URI*
- *SRCREV*
- *S*
- *inherit ...*
- *PACKAGECONFIG*
- variabili specifiche per la classe di build come *EXTRA\_OECONF*
- Tasks come *do\_configure*
- *PACKAGE\_ARCH*
- *PACKAGES*
- *FILES*
- *RDEPENDS*
- *RRECOMMENDS*
- *RSUGGESTS*
- *RPROVIDES*
- *RCONFLICTS*
- *BBCLASSEXTEND*

In alcuni casi, l'ordine è importante e in questi casi l'ordine di default viene sovrascritto. Ad esempio:

- `PACKAGE_ARCH` deve essere impostato prima di `inherit packagegroup`

I task devono essere ordinati in base all'ordine di esecuzione. Per i task di uso comune, l'ordine sarebbe:

- `do_fetch`
- `do_unpack`
- `do_patch`
- `do_prepare_recipe_sysroot`
- `do_configure`
- `do_compile`
- `do_install`
- `do_populate_sysroot`
- `do_package`

I task personalizzati devono essere ordinate in modo simile.

Le variabili specifiche del pacchetto sono generalmente raggruppate, ad esempio:

```
RDEPENDS:${PN} = "foo"
RDEPENDS:${PN}-libs = "bar"

RRECOMMENDS:${PN} = "one"
RRECOMMENDS:${PN}-libs = "two"
```

### Campi di Licenza della Ricetta

Le ricette devono definire entrambe le variabili `LICENSE` e `LIC_FILES_CHKSUM`:

- `LICENSE`: Questa variabile specifica la licenza del software. Se non si conosce la licenza con cui viene distribuito il software che si sta compilando, è necessario consultare il codice sorgente per trovare queste informazioni. I file tipici che contengono queste informazioni includono `COPYING`, `LICENSE` e `README`. È possibile trovare queste informazioni anche all'inizio di un file sorgente. Ad esempio, dato un software con licenza GNU General Public License versione 2, si imposterebbe `LICENSE` come segue:

```
LICENSE = "GPL-2.0-only"
```

Le licenze specificate in `LICENSE` possono avere qualsiasi nome, purché non contengano spazi, poiché questi vengono utilizzati come separatori tra i nomi delle licenze. Per le licenze standard, utilizzare i nomi dei file in `meta/files/common-licenses/` o i nomi dei flag `SPDXLICENSEMAP` definiti in `meta/conf/licenses.conf`.

#### Nota

Impostare una `LICENSE` in una ricetta si applica al software da compilare tramite quella ricetta, non al file della ricetta stessa. La licenza delle ricette, dei file di configurazione e degli script deve essere specificata



chiaramente, ad esempio tramite commenti o tramite una licenza presente nel *layer* che contiene questi file. Questi file di licenza si trovano solitamente nella directory principale del layer. Le eccezioni devono essere chiaramente indicate nel file README o nel file LICENSE del layer.

Ad esempio, il layer *OpenEmbedded-Core (OE-Core)* fornisce sia i file di licenza GPL-2.0-only che MIT, oltre a un file "LICENSE" che spiega come queste due licenze vengono attribuite ai file presenti nel layer.

- **LIC\_FILES\_CHKSUM**: Il sistema di build di OpenEmbedded utilizza questa variabile per verificare che il testo della licenza non sia cambiato. In caso contrario, la compilazione genera un errore, offrendoti la possibilità di individuarlo e correggerlo.

È necessario specificare tutti i file di licenza applicabili al software. Al termine della fase di configurazione, il processo di compilazione confronterà i checksum dei file per verificare che il testo non sia cambiato. Eventuali differenze genereranno un errore con un messaggio contenente il checksum corrente. Per ulteriori spiegazioni ed esempi su come impostare la variabile **LIC\_FILES\_CHKSUM**, consultare la sezione "*Tracking License Changes*".

Per determinare la stringa di checksum corretta, è possibile elencare i file appropriati nella variabile **LIC\_FILES\_CHKSUM** con stringhe MD5 errate, provare a compilare il software e quindi annotare i messaggi di errore risultanti che indicheranno le stringhe MD5 corrette. Consultare la sezione "*Fetching Code*" per ulteriori informazioni.

Ecco un esempio che presuppone che il software abbia un file COPYING:

```
LIC_FILES_CHKSUM = "file://COPYING;md5=xxx"
```

Quando si tenta di compilare il software, il sistema di build genererà un errore e fornirà la stringa corretta che è possibile sostituire nel file di configurazione per una compilazione successiva.

## Aggiornamenti delle Licenze

Quando si modificano i campi **LICENSE** o **LIC\_FILES\_CHKSUM** nella ricetta a seguito di modifiche apportate dal progetto originale ai file di licenza, è necessario spiegare brevemente il motivo della modifica tramite un tag `License-Update:`. Spesso si tratta di una spiegazione piuttosto semplice, ad esempio:

```
License-Update: copyright years refreshed
```

Meno frequentemente, i termini di licenza stessi potrebbero essere cambiati. In tal caso, si consiglia di fornire un link al progetto originale che ha preso/giustificato tale decisione.

Il tag `License-Update:` non è necessario per i commit che correggono dati di licenza errati nei nostri metadati (per un esempio, vedere il commit OE-Core [6c8b76d](#)).

## Suggerimenti e Linee Guida per la Scrittura di Ricette

- Utilizzare **BBCLASSEXTEND** invece di creare ricette separate come `-native` e `-nativesdk`, quando possibile. Questo evita di dover gestire più file di ricetta contemporaneamente.

- Le ricette dovrebbero contenere task idempotenti, ovvero l'esecuzione ripetuta di un determinato task non dovrebbe modificare il risultato finale. L'ambiente di compilazione si basa su questo presupposto e la sua violazione può causare errori di compilazione difficili da individuare.
- Per garantire l'idempotenza durante la modifica dei file nelle attività, è generalmente consigliabile:
  - copiare il file `X` in `X.orig` (solo se non esiste già)
  - quindi, copiare `X.orig` nuovamente in `X`,
  - e, infine, modificare `X`.

Questo garantisce che la riesecuzione del task produca sempre lo stesso risultato finale e che il file originale possa essere conservato per essere riutilizzato. Protegge inoltre dal rischio che un'interruzione della compilazione possa corrompere il file.

### 5.3.6 Stato della Patch Upstream

Per tenere traccia delle patch applicate dalle ricette e, in definitiva, ridurre il numero di patch da gestire, il sistema di build di OpenEmbedded richiede informazioni sullo stato di ciascuna patch nel progetto upstream [principale].

Nella sua descrizione, ogni patch dovrebbe fornire informazioni dettagliate sul bug che risolve, come l'URL in un sistema di tracciamento dei bug e i link agli archivi delle mailing list pertinenti.

Si dovrebbe anche aggiungere un tag `Upstream-Status: `` contenente una delle seguenti stringhe di stato:

#### **Pending**

Non è stata ancora presa alcuna decisione oppure la patch non è stata ancora inviata al progetto upstream.

Si tenga presente che ogni patch inviata al progetto upstream riduce il carico di manutenzione di OpenEmbedded e di Yocto Project a lungo termine, quindi questo stato della patch dovrebbe essere utilizzato solo in casi eccezionali in cui sussistono ostacoli reali all'invio di una patch al progetto upstream; la motivazione di tali ostacoli deve essere inclusa nella patch.

#### **Submitted [where]**

Inviata al progetto upstream, in attesa di approvazione. Facoltativamente, includi dove è stata inviata, ad esempio l'autore, la mailing list, ecc.

#### **Backport [version]**

Accettata dal progetto upstream e inclusa nella prossima release, oppure retroportata da una versione più recente del progetto upstream, poiché ci troviamo a una versione fissa. Includi le informazioni sulla versione del progetto upstream (ad esempio, ID del commit o prossima versione prevista).

#### **Denied**

Non accettata dal progetto upstream; includere la motivazione nella patch.

#### **Inactive-Upstream [lastcommit: when (and/or) lastrelease: when]**

Il progetto upstream non è più disponibile. In genere si tratta di un progetto abbandonato, inattivo da molto tempo, anche in anni. Per valutare la situazione, si consiglia di verificare non solo la data dell'ultima release, ma anche la data dell'ultimo commit e se le segnalazioni di bug e le richieste di merge effettuate da allora non hanno ricevuto risposta. Si consiglia inoltre di aggiungere alla descrizione della patch eventuali link pertinenti che mostrino chiaramente l'inattività.

**Inappropriate [reason]**

La patch non è appropriata per l'invio al progetto upstream. Si prega di includere una breve motivazione sulla stessa riga, racchiusa tra parentesi quadre []. In passato, esistevano diverse ragioni per non inviare patch al progetto upstream, ma dobbiamo considerare che ogni patch non inviata al progetto upstream rappresenta un onere di manutenzione per i manutentori delle ricette. Attualmente, le uniche ragioni per contrassegnare una patch come non appropriata per l'invio al progetto upstream sono:

- `oe specific`: il problema è specifico del modo in cui OpenEmbedded esegue le build o configura le cose in fase di runtime e può essere risolto solo con una patch che, tuttavia, non è rilevante o appropriata per l'invio generale al progetto upstream.
- `upstream ticket <link>`: il problema non è specifico di OpenEmbedded e dovrebbe essere risolto al progetto upstream, ma la patch nella sua forma attuale non è adatta per l'unione al progetto upstream e l'autore non possiede le competenze sufficienti per sviluppare una patch adeguata. Il problema viene quindi gestito tramite una segnalazione di bug (includere il link).

Naturalmente, se in seguito un'altra persona si occupa di inviare questa patch al progetto upstream, lo stato dovrebbe essere modificato in `Submitted [where]` e la persona che si assume la responsabilità dell'invio dovrebbe aggiungere alla patch una riga aggiuntiva con la dicitura `Signed-off-by:`.

**Esempi**

Ecco un esempio di patch inviata in upstream:

```
rpm: Adjusted the foo setting in bar

[RPM Ticket #65] -- http://rpm5.org/cvs/tktview?tn=65,5

The foo setting in bar was decreased from X to X-50% in order to
ensure we don't exhaust all system memory with foobar threads.

Upstream-Status: Submitted [rpm5-devel@rpm5.org]

Signed-off-by: Joe Developer <joe.developer@example.com>
```

Un futuro aggiornamento potrebbe modificare il valore in `Backport` o `Denied` a seconda dei casi.

Un altro esempio di patch specifica per OpenEmbedded:

```
Do not treat warnings as errors

There are additional warnings found with musl which are
treated as errors and fails the build, we have more combinations
than upstream supports to handle.

Upstream-Status: Inappropriate [oe specific]
```

Ecco una patch che è stata retroportata da un commit upstream:

```
include missing sys/file.h for LOCK_EX
```

```
Upstream-Status: Backport [https://github.com/systemd/systemd/commit/
↳ac8db36cbc26694ee94beecc8dca208ec4b5fd45]
```

### 5.3.7 Patch CVE

Per un migliore controllo delle vulnerabilità, le patch che risolvono le CVE devono contenere il tag `CVE:`. Questo tag dovrebbe elencare tutte le CVE risolte dalla patch. Se vengono risolte più CVE, separarle con degli spazi.

#### Esempi di CVE

Questo dovrebbe essere l'header della patch che risolve `CVE-2015-8370` in GRUB2:

```
grub2: Fix CVE-2015-8370

[No upstream tracking] -- https://bugzilla.redhat.com/show_bug.cgi?id=1286966

Back to 28; Grub2 Authentication

Two functions suffer from integer underflow fault; the grub_username_get() and
↳grub_password_get() located in
grub-core/normal/auth.c and lib/crypto.c respectively. This can be exploited to
↳obtain a Grub rescue shell.

Upstream-Status: Backport [http://git.savannah.gnu.org/cgit/grub.git/commit/?
↳id=451d80e52d851432e109771bb8febafca7a5f1f2]
CVE: CVE-2015-8370
Signed-off-by: Joe Developer <joe.developer@example.com>
```

### 5.3.8 Formato della Patch

Per default, le patch create con `git format-patch` hanno una firma di versione *Git* alla fine. Per evitare di avere una firma *Git* alla fine delle patch generate o aggiornate, è possibile utilizzare le impostazioni di configurazione di *Git*:

```
git config --global format.signature ""
```

**i Nota**

Le patch generate o aggiornate da `devtool` vengono create senza firma.

## 5.4 Apportare Modifiche a un Componente

I contributi a Yocto Project e a OpenEmbedded sono benvenuti. Dato che il sistema è estremamente configurabile e flessibile, sappiamo che gli sviluppatori vorranno estenderlo, configurarlo o ottimizzarlo per le loro esigenze specifiche.

### 5.4.1 Contribuire tramite mailing list: Perché non utilizzare flussi di lavoro basati sul web?

Sia Yocto Project che OpenEmbedded hanno molti componenti chiave che vengono mantenuti tramite patch inviate tramite mailing list. Sappiamo che questo approccio può sembrare un po' antiquato, considerando che sono disponibili altri flussi di lavoro basati su tecnologie web come GitHub, GitLab e altri. Poiché ci viene spesso posta questa domanda, abbiamo deciso di documentare i motivi per cui utilizziamo le mailing list.

Un fattore importante è che diamo valore alla revisione paritaria. Quando viene proposta una modifica a molti dei componenti principali del progetto, è utile che venga esaminata da più persone. Sebbene la decisione finale sull'accettazione o il rifiuto di una patch spetti a un singolo manutentore, la revisione viene effettuata da più persone e l'identità di chi la effettua è probabilmente sconosciuta al manutentore. Spesso è il revisore a sorpresa a individuare i problemi più interessanti!

Questo contrasta con il flusso di lavoro in stile "GitHub", dove la revisione viene effettuata solo dal manutentore o richiesta specificamente a persone designate. Crediamo che questo tipo di revisione tra pari apporti un valore significativo al codice sorgente e che abbandonare le mailing list sarebbe dannoso per il nostro codice.

Dobbiamo anche riconoscere che molti dei nostri sviluppatori sono abituati a questo flusso di lavoro tramite mailing list e lo utilizzano da anni, con strumenti e processi creati appositamente per questo scopo. Abbandonare questo sistema comporterebbe la perdita di persone chiave dal progetto, il che sarebbe a sua volta dannoso.

I progetti sono perfettamente consapevoli che i potenziali nuovi collaboratori trovano l'approccio tramite mailing list scoraggiante e preferirebbero un'interfaccia grafica basata sul web. Poiché non crediamo che questa soluzione possa funzionare per noi, il progetto si propone di rendere disponibile [patchwork](#) per aiutare a monitorare lo stato delle patch e sta anche valutando come gli strumenti possano fornire un feedback più completo agli utenti sullo stato delle patch. Stiamo cercando di migliorare strumenti come `patchtest` per testare i contributi degli utenti prima che vengano inviati alle mailing list e anche di documentare meglio come utilizzare tali flussi di lavoro, poiché riconosciamo che, mentre questo era di dominio pubblico dieci anni fa, potrebbe non esserlo più.

### 5.4.2 Preparazione delle Modifiche per l'Invio

#### Configurazione di Git

La prima cosa da fare è installare i pacchetti Git. Ecco un esempio su Debian e Ubuntu:

```
sudo apt install git-core git-email
```

Successivamente, è necessario impostare un nome e un indirizzo e-mail che Git utilizzerà per identificare i commit:

```
git config --global user.name "Ada Lovelace"
git config --global user.email "ada.lovelace@gmail.com"
```

Per default, Git aggiunge una riga di firma alla fine delle patch contenente la versione di Git. Si consiglia di rimuoverla in quanto non aggiunge informazioni utili.

Rimuoverla con il seguente comando:

```
git config --global format.signature ""
```

### Clonare il repository Git del componente da modificare

Dopo aver identificato il componente da modificare come descritto nella sezione "*Identificazione del Componente*", clonare il repository Git corrispondente. Ecco un esempio per OpenEmbedded-Core:

```
git clone https://git.openembedded.org/openembedded-core
cd openembedded-core
```

### Creare un nuovo branch

Poi, si crea un nuovo branch nel proprio repository Git locale per le modifiche, partendo dal branch di riferimento nel repository upstream (spesso chiamato `master`):

```
$ git checkout <ref-branch>
$ git checkout -b my-changes
```

Se si ha un set di modifiche completamente indipendenti da inviare, si dovrebbe addirittura creare un branch per ogni set.

### Implementare e confermare le modifiche

In ogni branch, si deve raggruppare le proprie modifiche in piccole parti controllate e isolate. Mantenere le modifiche piccole e isolate facilita la revisione, semplificare le operazioni di merge/rebase e mantenere pulita la cronologia delle modifiche, qualora qualcuno dovesse farvi riferimento in futuro.

A questo scopo, si deve creare *un commit Git per ogni modifica*, corrispondente a ciascuna delle patch che si invierà. Consultare [ulteriori indicazioni](#) nella documentazione del kernel Linux, se necessario.

Ad esempio, quando si intende aggiungere più nuove ricette, ciascuna ricetta deve essere aggiunta in un commit separato. Per gli aggiornamenti di ricette esistenti, la versione precedente dovrebbe in genere essere eliminata come parte dello stesso commit per aggiungere la versione aggiornata.

1. *Staging delle Modifiche:* Aggiungere le modifiche all'area di staging utilizzando il comando `git add` su ogni file modificato. Per aggiungere tutti i file modificati all'area di staging, si può anche utilizzare il comando `git add -A`.
2. *Commit delle Modifiche:* In questa fase si possono creare commit separati. Per ogni commit da creare, si utilizza il comando `git commit -s` specificando i file o le directory da includere nel commit:

```
$ git commit -s file1 file2 dir1 dir2 ...
```

Per includere tutti i file aggiunti all'area di staging:

```
$ git commit -sa
```

1. L'opzione `-s` di `git commit` aggiunge la riga "Signed-off-by:" al messaggio di commit. Lo stesso requisito vale per chi contribuisce al kernel Linux. L'aggiunta di tale riga indica che l'utente che invia la patch ha accettato il [Developer's Certificate of Origin 1.1](#) come segue:

Developer's Certificate of Origin 1.1

By making a contribution to this project, I certify that:

- (a) The contribution was created in whole or in part by me and I have the right to submit it under the open source license indicated in the file; or
- (b) The contribution is based upon previous work that, to the best of my knowledge, is covered under an appropriate open source license and I have the right under that license to submit that work with modifications, whether created in whole or in part by me, under the same open source license (unless I am permitted to submit under a different license), as indicated in the file; or
- (c) The contribution was provided directly to me by some other person who certified (a), (b) or (c) and I have not modified it.
- (d) I understand and agree that this project and the contribution are public and that a record of the contribution (including all personal information I submit with it, including my sign-off) is maintained indefinitely and may be redistributed consistent with this project or the open source license(s) involved.

2. Fornire un breve riepilogo della modifica su una sola riga e, se sono necessarie ulteriori spiegazioni, aggiungere maggiori dettagli nella descrizione del commit. Questo riepilogo è generalmente visibile nella "shortlist" delle modifiche. Pertanto, fornire una descrizione breve e concisa che riassume la modifica è utile quando si visualizza un elenco di molti commit. Anteporre a questa breve descrizione il nome della ricetta (se si modifica una ricetta) o il path abbreviato del file modificato.

**Nota**

Per trovare un prefisso adatto per il riepilogo del commit, un buon consiglio è quello di cercare i prefissi utilizzati nei commit precedenti che hanno interessato gli stessi file o directory:

```
git log --oneline <paths>
```

3. Nella descrizione del commit, fornire informazioni dettagliate che descrivano cosa è stato modificato, perché è stato fatto e l'approccio che utilizzato. Potrebbe anche essere utile menzionare come è stata testata la modifica. Fornire il maggior numero possibile di dettagli nella descrizione del commit.

**Nota**

Se il riepilogo di una sola riga è sufficiente a descrivere una modifica semplice, la descrizione del commit può essere lasciata vuota.

4. Se la modifica risolve un bug o un problema specifico associato a un ID di tracciamento dei bug, includere un riferimento a tale ID nel corpo del messaggio di commit. Ad esempio, Yocto Project utilizza una convenzione specifica per i riferimenti ai bug: qualsiasi commit che risolve un bug specifico dovrebbe utilizzare il seguente formato per il corpo del messaggio di commit. Assicurarsi di utilizzare l'ID di tracciamento del bug effettivo di Bugzilla per bug-id:

```
single-line summary of change
```

```
Fixes [YOCTO #bug-id]
```

```
detailed description of change
```

5. Se altre persone hanno partecipato a questa patch, aggiungere alcuni tag alla descrizione del commit per dare credito agli altri contributori alla modifica:
  - **Reported-by:** nome e indirizzo email della persona che ha segnalato un bug che il commit sta cercando di correggere. Questa è una buona pratica per incoraggiare gli utenti a continuare a segnalare bug e far loro sapere che le loro segnalazioni vengono prese in considerazione.
  - **Suggested-by:** nome e indirizzo email della persona a cui attribuire il merito dell'idea di apportare la modifica.
  - **Tested-by, Reviewed-by:** nome e indirizzo email delle persone che hanno testato le modifiche o revisionato il codice. Questi campi vengono solitamente aggiunti dal manutentore che accetta una patch, oppure in proprio se si è il mittente delle patch a dei revisori preliminari o se si sta inviando nuovamente una patch non modificata come parte di una nuova iterazione della propria serie di patch.
  - **Cc:** nome e indirizzo email delle persone a cui inviare una copia delle modifiche. Questo campo verrà utilizzato da `git send-email`.

Per, [ulteriori informazioni sull'utilizzo di questi tag](#) consultare la documentazione del kernel Linux.



**Nota**

È possibile modificare un messaggio di commit Git esistente per aggiungere i tag mancanti per i collaboratori con il comando `git commit --amend`.

**Verificare le modifiche**

Per ogni contributo che apporti, si devono anche testare le modifiche. A tal fine, Yocto Project offre diversi tipi di test. Questi test coprono aree diverse e la loro fattibilità dipende dalle modifiche che apportata. Ad esempio, eseguire:

- Per modifiche che interessano l'ambiente di build:
  - `bitbake-selftest`: per le modifiche all'interno di BitBake
  - `oe-selftest`: per testare combinazioni di esecuzioni di BitBake
  - `oe-build-perf-test`: per testare le prestazioni di scenari di compilazione comuni
- Per modifiche a una ricetta:
  - `ptest`: esegue test specifici del pacchetto, se presenti
  - `testimage`: creare un'immagine, avviarla ed eseguirci i test
  - Se applicabile, eseguire anche le build delle varianti `native` e `nativesdk`
- Per modifiche relative all'SDK:
  - `testsdk`: per compilare, installare ed eseguire test su un SDK
  - `testsdk_ext`: per compilare, installare ed eseguire test su un SDK esteso

Si noti che questo elenco fornisce solo suggerimenti e non è esaustivo. Maggiori dettagli sono disponibili qui: [Yocto Project Tests --- Types of Testing Overview](#).

**5.4.3 Creazione di Patch**

Ecco la procedura generale per creare patch da inviare via email:

1. *Descrivere le Modifiche nel Proprio Branch*: Se il branch contiene più di un commit, si consiglia di allegare una lettera di presentazione che descriva la serie di patch inviata.

A questo scopo, una buona soluzione è quella di salvare il contenuto della lettera di presentazione direttamente nel branch:

```
git branch --edit-description
```

Questo aprirà un editor di testo in cui si potrà inserire la descrizione delle modifiche. Questa descrizione può essere aggiornata quando necessario e verrà utilizzata da Git per creare la lettera di presentazione insieme alle patch.

Si consiglia di iniziare la descrizione con un titolo che fungerà da oggetto per la lettera di presentazione.

2. *Generare le Patch per il Branch*: Il comando `git format-patch` genererà i file patch per ogni commit del branch. È necessario specificare il branch di riferimento da cui parte il branch.

Se il branch non necessitava di una descrizione nel passaggio precedente:

```
$ git format-patch <ref-branch>
```

Se invece è stata inserita una descrizione per il branch, si dovrà generare anche una lettera di presentazione:

```
$ git format-patch --cover-letter --cover-from-description=auto <ref-branch>
```

Dopo l'esecuzione del comando, la directory corrente conterrà file `.patch` numerati per i commit del branch. Se c'è una lettera di presentazione, la si troverà nel file `0000-cover-letter.patch`.

#### Nota

L'opzione `--cover-from-description=auto` fa sì che `git format-patch` utilizzi il primo paragrafo della descrizione del branch come titolo della lettera di presentazione. Un'altra possibilità, più facile da ricordare, è quella di passare solo l'opzione `--cover-letter`, ma si dovrà modificare manualmente l'oggetto ogni volta che si generano le patch.

Consultare la [pagina del manuale di git](#) per maggiori dettagli.

3. *Rivedere Ogni File di Patch*: Questa revisione finale delle patch prima dell'invio consente spesso di visualizzare le modifiche da una prospettiva diversa e di individuare difetti come errori di battitura, problemi di spaziatura o di riga, o persino file che non si intendevano modificare. Questa revisione dovrebbe includere anche la patch della lettera di presentazione.

Se necessario, rielaborare i propri commit come descritto in "*Considerazioni sulla Revisione delle Patch*".

## 5.4.4 Validazione delle Patch con Patchtest

`patchtest` è disponibile in `openembedded-core` come strumento per garantire che le patch siano ben formattate e contengano informazioni importanti per la manutenzione, come la presenza di `Signed-off-by`. Si noti che `patchtest` non eseguirà alcun test funzionale delle modifiche. Attualmente, supporta solo il test delle patch per i branch di `openembedded-core`. Per configurarlo, procedere come segue:

```
pip install -r meta/lib/patchtest/requirements.txt
source oe-init-build-env
bitbake-layers add-layer ../meta-selftest
```

Una volta completati questi passaggi e generati i file delle patch, è possibile eseguire `patchtest` in questo modo:

```
patchtest --patch <patch_name>
```

In alternativa, se si desidera che `patchtest` esegua un'iterazione e testi più patch memorizzate in una directory, è possibile utilizzare:

```
patchtest --directory <directory_name>
```

Per default, `patchtest` utilizza i path dei file dei propri moduli per determinare il repository e la suite di test da utilizzare per il controllo delle patch. Per testare le patch su un repository diverso da `openembedded-core` e/o utilizzare un set di test diverso, si possono usare i flag `--reporidir` e `--testdir`:

```
patchtest --patch <patch_name> --reporidir <path/to/repo> --testdir <path/to/testdir>
```

Infine, si tenga presente che `patchtest` è progettato per testare le patch in modo indipendente, quindi se le patch devono essere applicate sopra le modifiche apportate da patch precedenti in una serie, è possibile che `patchtest` segnali falsi errori relativi al test "merge on head".

L'utilizzo di `patchtest` in questo modo fornisce un controllo finale sulla qualità complessiva delle modifiche prima che vengano inviate per la revisione da parte dei manutentori.

## 5.4.5 Invio delle Patch via Email

### Utilizzo di Git per Inviare le Patch

Per inviare patch via email, è fondamentale che non contengano spazi bianchi o formattazione HTML, né introdotti manualmente né dal client di posta. Il manutentore che riceve le patch deve essere in grado di salvarle e applicarle direttamente dalle email, utilizzando il comando `git am`.

L'utilizzo del comando `git send-email` è l'unico modo sicuro per inviare patch via email, poiché elimina il rischio di compromettere la formattazione degli spazi bianchi nel corpo del messaggio, cosa che può accadere utilizzando il proprio client di posta. Inoltre, includerà correttamente le patch come *inline attachments*, cosa non facile da fare con i client di posta elettronica standard senza mandare a capo il testo. Utilizzando il normale client di posta elettronica e condividendo le patch come allegati, i revisori non sarebbero in grado di citare sezioni specifiche delle modifiche e di commentarle.

### Configurazione di Git per l'Invio di Email

Il comando `git send-email` può inviare email utilizzando un Mail Transport Agent (MTA) locale o remoto, come `msmtp`, `sendmail`, oppure tramite una configurazione SMTP diretta nel file `~/.gitconfig` di Git.

Ecco le impostazioni per consentire a `git send-email` di inviare email tramite il tuo server SMTP abituale, utilizzando un account Google Mail come esempio:

```
git config --global sendemail.smtpserver smtp.gmail.com
git config --global sendemail.smtpserverport 587
git config --global sendemail.smtpencryption tls
git config --global sendemail.smtpuser ada.lovelace@gmail.com
git config --global sendemail.smtppass = XXXXXXXX
```

Queste impostazioni appariranno nel file `.gitconfig` nella propria directory home.

Se non si può utilizzare né un MTA locale né SMTP, si deve utilizzare un client di posta elettronica che non modifichi il messaggio (invertendo gli spazi in tabulazioni, mandando a capo le righe, ecc.). Un buon client di posta per questo scopo è Pine (o Alpine) o Mutt. Per ulteriori informazioni sui client compatibili, consultare la sezione [Informazioni sui client di posta elettronica per Linux](#) nei sorgenti del kernel Linux.

Se si utilizzano client di questo tipo, è sufficiente includere la patch nel corpo dell'e-mail.

## Trovare una Mailing List Adatta

È necessario inviare le patch alla mailing list appropriata affinché possano essere esaminate dai collaboratori competenti e integrate dal manutentore di riferimento. La mailing list specifica da utilizzare dipende dalla posizione del codice che si sta modificando.

Se qualcuno ha dubbi su una qualsiasi delle patch, di solito li esprime tramite la mailing list. Se le patch non ricevono recensioni negative, il manutentore del layer interessato in genere le prende, le testa e, in base all'esito positivo dei test, le integra.

In generale, ogni componente (ad esempio, un layer) dovrebbe avere un file `README` che indica dove inviare le modifiche e quale procedura seguire.

Se si intende inviare una nuova ricetta che non rientra né in *OpenEmbedded-Core (OE-Core)*, né in *meta-openembedded*, è necessario cercare un layer adatto su <https://layers.openembedded.org>. Se si prevedono ricette simili, si può consultare la sezione *Creating Your Own Layer*.

In caso di dubbi, si prega di chiedere sulla mailing list generale *yocto* o sulla mailing list *openembedded-devel*.

## Iscrizione alla Mailing List

Dopo aver individuato la mailing list più adatta, si dovrà iscriversi se non già fatto.

Se si tenta di inviare patch a una lista a cui non si è iscritti, l'email verrà restituita come non recapitata.

Tuttavia, se non si desidera ricevere tutti i messaggi inviati a una mailing list, si può impostare l'iscrizione su "no email". Si rimarrà comunque iscritti e si potranno inviare messaggi, ma non si riceveranno email. Se qualcuno risponde al messaggio, il suo client di posta elettronica includerà automaticamente il proprio indirizzo email nella conversazione.

In ogni caso, si potrà accedere ai nuovi messaggi negli archivi delle mailing list, tramite un browser web oppure, per le liste archiviate su <https://lore.kernel.org>, tramite un feed di newsgroup individuale o un repository Git.

## Invio delle Patch via Email

A questo punto, si è pronti per inviare le patch via email. Ecco l'utilizzo tipico di `git send-email`:

```
git send-email --to <mailing-list-address> *.patch
```

Successivamente, rivedere attentamente ogni riga dell'oggetto e l'elenco dei destinatari, quindi consentire al comando di inviare ogni messaggio.

Si noterà che `git send-email` invierà automaticamente una copia a tutti i destinatari indicati nei tag di commit, come `Signed-off-by` o `Reported-by`.

Nel caso in cui si stia inviando patch per *meta-openembedded* o per qualsiasi altro layer diverso da *openembedded-core*, aggiungere il prefisso appropriato in modo che sia chiaro a quale layer deve essere applicata la patch:

```
git format-patch --subject-prefix="meta-oe" [PATCH] ...
```

**i Nota**

È possibile inviare patch anche senza generarle prima. Tuttavia, assicurarsi di aver esaminato attentamente le modifiche, perché `git send-email` mostrerà solo le righe del titolo di ciascuna patch.

Ecco un comando utilizzabile se è stata cambiata una sola patch nel proprio branch:

```
git send-email --to <mailing-list-address> -1
```

Se si hanno più patch e una lettera di presentazione, si possono inviare le patch per tutti i commit tra il branch di riferimento e la fine del proprio branch:

```
git send-email --cover-letter --cover-from-description=auto --to <mailing-list-  
→address> -M <ref-branch>
```

Consultare la [pagina del manuale di send-email di git](#) per maggiori dettagli.

## Risoluzione dei Problemi Relativi alle Email

### Correzione dell'Identità del Mittente

Abbiamo un problema frequente con i collaboratori le cui patch vengono ricevute tramite un campo `From` che non corrisponde alle informazioni `Signed-off-by`. Ecco un esempio tipico per chi invia da un nome di dominio con <https://en.wikipedia.org/wiki/DMARC>:

```
From: "Linus Torvalds via lists.openembedded.org <linus.torvalds@kernel.org@lists.  
→openembedded.org>"
```

Questo campo `From` viene utilizzato da `git am` per ricreare i commit con il nome dell'autore corretto. Quanto segue garantirà che le e-mail abbiano un campo `From` aggiuntivo all'inizio del corpo dell'e-mail, in modo che i manutentori che accettano le patch non debbano correggere manualmente le informazioni sull'autore del commit:

```
git config --global sendemail.from "linus.torvalds@kernel.org"
```

Il campo `sendemail.from` deve corrispondere all'impostazione `user.email`, che appare nella riga `Signed-off-by` dei commit.

### Ottimizzazione dell'utilizzo di "git send-email"

Per risparmiare tempo ed evitare di dover ricordare le opzioni corrette da utilizzare con `git send-email`, si possono utilizzare le impostazioni di configurazione di Git.

- Per impostare l'indirizzo corretto della mailing list per un determinato repository:

```
git config --local sendemail.to openembedded-devel@lists.openembedded.org
```

- Se la mailing list richiede un prefisso per l'oggetto del layer (questo funziona solo se il repository contiene un solo layer):

```
git config --local format.subjectprefix "meta-something" [PATCH"
```

### 5.4.6 Uso di Script per il Push di una Modifica Upstream e il Pull Request

Per serie di patch più ampie, è preferibile inviare una pull request che includa non solo la patch, ma anche un puntatore a un branch da cui prelevare le modifiche. Questo comporta la creazione di un branch locale per le modifiche, il push di questo branch in un repository accessibile e quindi l'utilizzo degli script `create-pull-request` e `send-pull-request` di `openembedded-core` per creare e inviare una serie di patch con un link al branch per la revisione.

Seguire questa procedura per inviare una modifica a un repository Git "contrib" upstream dopo aver seguito i passaggi descritti in "*Preparazione delle Modifiche per l'Invio*":

#### Nota

Si possono trovare informazioni generali su Git e su come inviare una modifica upstream nel [Git Community Book](#).

1. *Richiedere l'Accesso in Push a un Repository "Upstream" Contrib:* Inviare un'email a `helpdesk@yoctoproject.org`:
  - Allegare la propria chiave pubblica SSH, che di solito si chiama `id_rsa.pub`. Se non se ne possiede una, generala eseguendo `ssh-keygen -t rsa -b 4096 -C "your_email@example.com"`.
  - Elencare i repository a cui si intende contribuire.
  - Includere il prefisso del branch che si preferisce per i repository `-contrib`.
2. *Eseguire il Push dei Commit al Repository "Contrib" Upstream:* Eseguire il push delle modifiche a quel repository:

```
$ git push upstream_remote_repo local_branch_name
```

Ad esempio, supponiamo che si abbiano i permessi per eseguire il push nel repository upstream `meta-intel-contrib` e che si stia lavorando in un branch locale chiamato `your_name/README`. Il seguente comando invia i propri commit locali al repository upstream `meta-intel-contrib` e li inserisce in un branch denominato `your_name/README`:

```
$ git push meta-intel-contrib your_name/README
```

3. *Determinare a Chi Notificare:* Determinare il manutentore o la mailing list a cui notificare la modifica.

Prima di inviare qualsiasi modifica, ci si deve accertare di chi sia il manutentore o a quale mailing list inviare la notifica. Utilizzare uno di questi metodi per scoprirlo:

- *File di Manutenzione:* Esaminare il file `maintainers.inc`, che si trova in *OpenEmbedded-Core (OE-Core)* in `meta/conf/distro/include`, per vedere chi è responsabile del codice.
- *Ricerca per File:* Utilizzando *Git*, è possibile inserire il seguente comando per visualizzare un breve elenco di tutti i commit relativi a un file specifico:

```
git shortlog -- filename
```

Basta fornire il nome del file di interesse. Le informazioni restituite non sono ordinate cronologicamente, ma includono un elenco di tutti coloro che hanno effettuato commit, raggruppati per nome. Dall'elenco, è possibile vedere chi è responsabile della maggior parte delle modifiche al file.

- *Trovare la Mailing List da Utilizzare:* Consultare la sezione "[Trovare una Mailing List Adatta](#)" sopra.

4. *Creare una Pull Request:* Notificare al manutentore o alla mailing list di aver inviato una modifica creando una pull request.

Yocto Project fornisce due script che consentono di generare e inviare facilmente pull request a Yocto Project. Questi script sono `create-pull-request` e `send-pull-request`. Si trovano nella directory `scripts` in *OpenEmbedded-Core (OE-Core)*.

L'utilizzo di questi script formatta correttamente le richieste senza introdurre spazi bianchi o formattazione HTML. Il manutentore che riceve le patch, direttamente o tramite la mailing list, deve essere in grado di salvarle e applicarle direttamente dalle e-mail. Questo è il metodo preferito per l'invio delle patch.

Innanzitutto, si crea la pull request. Ad esempio, il seguente comando esegue lo script, specifica il repository upstream nella directory `contrib` in cui si è effettuato il push della modifica e fornisce un oggetto nei file patch creati:

```
$ ./scripts/create-pull-request -u meta-intel-contrib -s "Updated Manual
→Section Reference in README"
```

L'esecuzione di questo script crea file `*.patch` in una cartella denominata `pull-PID` nella directory corrente. Uno dei file patch è una lettera di presentazione.

Prima di eseguire lo script `send-pull-request`, è necessario modificare la patch della lettera di presentazione per inserire le informazioni sulla modifica. Dopo aver modificato la lettera di presentazione, si invia la pull request. Ad esempio, il seguente comando esegue lo script e specifica la directory della patch e l'indirizzo email. In questo esempio, l'indirizzo email è quello di una mailing list:

```
$ ./scripts/send-pull-request -p ~/meta-intel/pull-10565 -t meta-intel@lists.
→yoctoproject.org
```

È necessario seguire le istruzioni visualizzate, poiché lo script è interattivo.

**i Nota**

Per ricevere assistenza sull'utilizzo di questi script, è sufficiente specificare l'argomento `-h` come segue:

```
$ ./scripts/create-pull-request -h
$ ./scripts/send-pull-request -h
```

## 5.4.7 Invio di Modifiche ai Branch di Rilascio Stabili

La procedura per proporre modifiche a un branch stabile di Yocto Project differisce dai passaggi descritti sopra. Le modifiche a un branch stabile devono risolvere bug o CVE identificati e devono essere apportate con attenzione per evitare il rischio di introdurre nuovi bug o compromettere la compatibilità con le versioni precedenti. In genere, le correzioni di bug devono essere già state accettate nel branch master prima di poter essere retroportate a un branch stabile, a meno che il bug in questione non influisca sul branch master o la correzione sul branch master non sia adatta al "backporting" [retroportazione].

L'elenco dei branch stabili, insieme allo stato e al manutentore di ciascun branch, è disponibile nella pagina [Releases](#).

**i Nota**

Le patch inviate per un branch stabile devono essere modifiche isolate, leggibili e comprensibili. Le correzioni per CVE o altri problemi di elevata complessità, che consistono in un numero elevato di commit e/o un numero elevato di righe modificate, difficilmente verranno accettate a causa delle difficoltà che comportano in termini di manutenibilità e scalabilità.

In genere, le modifiche non vengono accettate per i branch contrassegnati come End-Of-Life (EOL).

Tenendo presente questo, i passaggi per inviare una modifica per un branch stabile sono i seguenti:

1. *Identificare il bug o la CVE da correggere:* Queste informazioni devono essere raccolte in modo da poter essere incluse nella richiesta di modifica.

Consultare [Verifica delle Vulnerabilità](#) per i dettagli sul tracciamento delle CVE.

2. *Verificare se la correzione è già presente nel branch master:* Questo consentirà di individuare il path più semplice per l'integrazione della correzione nel branch stabile.

1. *Se la correzione è presente nel branch master, inviare una richiesta di backport via email:* È necessario inviare un'e-mail al manutentore del branch stabile di riferimento e alla mailing list con i dettagli del bug o della CVE da correggere, l'hash del commit sul branch master che risolve il problema e i branch stabili su cui si desidera che la correzione venga retroportata.
2. *Se la correzione non è presente nel branch master, inviarla prima al branch master:* Questo garantirà che la correzione superi i normali processi di revisione e test delle patch del progetto prima di essere accettata. Inoltre, assicurerà che non rimangano bug irrisolti nel branch master stesso. Una volta che la correzione è stata accettata nel branch master, è possibile inviare una richiesta di backport come descritto sopra.
3. *Se la correzione non è adatta al branch master, si invia una patch direttamente al branch stabile:* Questo metodo dovrebbe essere considerato come ultima risorsa. In genere è necessario quando il branch master utilizza una versione più recente del software che include una correzione upstream per il problema o



quando il problema è stato risolto sul branch master in un modo che introduce modifiche incompatibili con le versioni precedenti. In questo caso, si seguono i passaggi descritti in "[Preparazione delle Modifiche per l'Invio](#)" e nelle sezioni seguenti, ma si modifica l'oggetto dell'e-mail della patch includendo il nome del branch stabile a cui si sta indirizzando la patch. Questo può essere fatto utilizzando l'argomento `--subject-prefix` di `git format-patch`, ad esempio per inviare una patch al branch "wrynose" utilizzare:

```
git format-patch --subject-prefix='wrynose' [PATCH] ...
```

### 5.4.8 Considerazioni sulla Revisione delle Patch

Si potrebbe ricevere feedback sulle patch inviate da altri membri della community o dal servizio automatico di test delle patch. Se vengono identificati problemi nelle proprie patch, di solito è necessario risolverli prima che le patch vengano accettate nel progetto. In questo caso, si devono rivedere i propri commit in base al feedback e inviare una versione aggiornata alla mailing list pertinente.

In ogni caso, non correggere mai i problemi segnalati modificandoli in nuovi commit sul proprio branch. Creare sempre una nuova serie di commit senza i problemi segnalati.

#### Nota

È buona norma inviare una copia ai revisori che hanno fornito feedback sulla versione precedente della patch. Ciò avviene aggiungendo un tag CC alla descrizione del commit:

```
CC: William Shakespeare <bill@yoctoproject.org>
```

Una singola patch può essere modificata usando `git commit --amend`, e più patch possono essere facilmente rielaborate e riordinate tramite un rebase interattivo di Git:

```
git rebase -i <ref-branch>
```

Consultare questo tutorial [this tutorial](#) per una guida pratica sull'utilizzo del rebase interattivo di Git.

Si deve anche modificare il tag `[PATCH]` nell'oggetto dell'email quando si invia la patch rivista per contrassegnare la nuova iterazione come `[PATCH v2]`, `[PATCH v3]`, ecc. a seconda dei casi. Questo può essere fatto passando l'argomento `-v` a `git format-patch` con un numero di versione:

```
git format-patch -v2 <ref-branch>
```

Dopo aver generato patch aggiornate (v2, v3 e così via) tramite `git format-patch`, idealmente gli sviluppatori dovrebbero aggiungere un changelog della versione della patch a ciascuna patch, che descriva le modifiche apportate tra le varie revisioni. Aggiungere il changelog della versione della patch dopo il marcatore `---` nella patch, indicando che queste informazioni fanno parte della patch stessa, ma non sono adatte per essere incluse nel messaggio di commit (ovvero nella cronologia di Git). Fornire un changelog della versione della patch facilita la comprensione sintetica delle modifiche apportate in tutte le versioni della patch da parte di manutentori e revisori, senza dover consultare fonti di informazione alternative, come ad esempio la ricerca tra i messaggi di una mailing list. Ad esempio:

```
<patch title>

<commit message>

<Signed-off-by/other trailers>
---
changes in v4:
- provide a clearer commit message
- fix spelling mistakes

changes in v3:
- replace func() to use other_func() instead

changes in v2:
- this patch was added in v2
---
<diffstat output>

<unified diff>
```

Infine, si devono testare anche le modifiche apportate. In particolare, non ci si limiti a modificare il file di patch generato da `git format-patch` e a inviarlo nuovamente.

## 5.4.9 Monitoraggio dello Stato delle Patch

Yocto Project utilizza un'istanza di [Patchwork](#) per monitorare lo stato delle patch inviate alle varie mailing list e per supportare il test automatico delle patch. Ogni patch inviata viene controllata per individuare errori comuni e deviazioni dal formato previsto, e gli autori vengono avvisati da `patchtest` se vengono rilevati tali errori. Questo processo contribuisce a ridurre il carico di lavoro dei manutentori per la revisione delle patch.

### Nota

Questo sistema non è perfetto e a volte le modifiche possono andare perse. È opportuno chiedere informazioni sullo stato di una patch o di una modifica se questa è rimasta inattiva per un po' di tempo senza alcun feedback.

Se le patch non hanno ricevuto alcun feedback per alcuni giorni, potrebbero essere già state integrate. Si può eseguire `git pull branch` per verificarlo. Da tener presente che molti, se non la maggior parte, dei manutentori dei layer non inviano email di conferma quando accettano una patch. In alternativa, se non c'è risposta o integrazione dopo alcuni giorni, la patch potrebbe essere stata trascurata o i revisori appropriati potrebbero non essere disponibili al momento. È quindi perfettamente lecito rispondere personalmente con un promemoria per richiedere un feedback.

**i Nota**

Le revisioni delle patch per gli aggiornamenti di funzionalità e ricette potrebbero subire ritardi durante un blocco delle funzionalità, poiché questo tipo di patch non viene unito in quel periodo; potrebbe essere necessario attendere la revoca del blocco.

I manutentori utilizzano comunemente anche i branch `-next` per testare le modifiche prima di unire le patch. Pertanto, è possibile farsi un'idea dello stato di una patch in base al fatto che sia stata unita o meno a uno di questi branch. I branch di test comunemente utilizzati per OpenEmbedded-Core sono i seguenti:

- *openembedded-core "master-next" branch*: Questo branch fa parte del repository [openembedded-core](#) e contiene le modifiche proposte ai metadati del core.
- *bitbake "master-next" branch*: Questo branch fa parte del repository [bitbake](#) e contiene modifiche a [BitBake](#).
- *meta-yocto "master-next" branch*: Questo branch fa parte del repository [meta-yocto](#) e contiene le modifiche proposte per meta-yocto.

Analogamente, i branch stabili gestiti dal progetto possono avere corrispondenti branch `-next` che raccolgono le modifiche proposte. Ad esempio, i branch `blacksail-next` e `wrynose-next` nei repository "openembedded-core" e "meta-yocto".

Altri layer possono avere branch di test simili, ma non esiste un requisito o uno standard formale in merito, quindi si deve di consultare la documentazione dei layer a cui si sta contribuendo.

#### 5.4.10 Accettazione del Codice Generato dall'IA

Yocto Project e OpenEmbedded seguono le linee guida della Linux Foundation per quanto riguarda l'utilizzo di strumenti di IA generativa. Vedere: <https://www.linuxfoundation.org/legal/generative-ai>.

È necessario seguire tutte le linee guida presenti in questo documento, incluse quelle contenute nella [Guida di Stile per le Ricette](#), e contribuire con modifiche e requisiti aggiuntivi agli elementi nella sezione [Implementare e confermare le modifiche](#).

Tutto il codice generato dall'IA deve essere etichettato come tale nel messaggio di commit, prima della riga `Signed-off-by`. Si raccomanda inoltre vivamente che qualsiasi patch o codice all'interno del commit contenga un commento o un'altra indicazione che specifichi che tale codice è stato generato dall'IA.

Ad esempio, ecco un messaggio di commit formattato correttamente:

```
component: Add the ability to ...

AI-Generated: Uses GitHub Copilot

Signed-off-by: Your Name <your.name@domain>
```

La riga `Signed-off-by` deve essere scritta da un umano e non dall'IA. Come promemoria, quando si contribuisce con una modifica, è richiesta la riga `Signed-off-by` e le disposizioni contenute nella [Developer's Statement of Origin 1.1](#) rimangono valide.

Inoltre, è necessario specificare che i contributi relativi all'IA siano conformi alle politiche della Linux Foundation, in particolare:

1. I contributori devono assicurarsi che i termini e le condizioni dello strumento di IA generativa non impongano restrizioni contrattuali sull'utilizzo dell'output dello strumento che siano incompatibili con la licenza del software open source del progetto, le politiche sulla proprietà intellettuale del progetto o la Definizione di Open Source.
  2. Qualora l'output dello strumento di intelligenza artificiale includa materiale protetto da copyright preesistente (incluso codice open source preesistente) di proprietà o creato da terzi, prima di contribuire al progetto, il Contributore deve accertarsi di aver ottenuto l'autorizzazione dai proprietari terzi –ad esempio tramite una licenza open source o una dichiarazione di pubblico dominio conforme alle politiche di licenza del progetto –per utilizzare e modificare tale materiale preesistente e contribuire al progetto. Inoltre, il Contributore deve fornire, insieme al proprio contributo, una notifica e l'attribuzione di tali diritti di terzi, unitamente alle informazioni sui termini di licenza applicabili.
- 

The Yocto Project ®

<[docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org)>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.

## 6.1 Requisiti di Sistema

Benvenuti nel Manuale di Riferimento di Yocto Project. Questo manuale fornisce informazioni di riferimento per la versione corrente di Yocto Project ed è più efficace se si hanno familiarità con i concetti di base del progetto. Il manuale non deve essere letto come punto di partenza per Yocto Project, né dall'inizio alla fine. Piuttosto, va utilizzato per trovare definizioni di variabili, descrizioni di classi e così via, a seconda delle necessità durante l'utilizzo di Yocto Project.

Per informazioni introduttive su Yocto Project, consultate il [Sito Web di Yocto Project](#) e il capitolo "*L'Ambiente di Sviluppo di Yocto Project*" nel Manuale Introduttivo e Concetti di Yocto Project.

Per utilizzare Yocto Project per creare rapidamente un'immagine senza dover comprendere i concetti, consultate il documento *Build Rapida di un'Immagine con lo Yocto Project*. Le istruzioni pratiche sono disponibili nel file *Manuale di Sviluppo dei Task di Yocto Project*. Una panoramica di Yocto Project e informazioni concettuali sono disponibili nel file *Manuale Introduttivo e Concetti di Yocto Project*.

**i Nota**

Per ulteriori informazioni sulla documentazione di Yocto Project, consultare la sezione *Links and Related Documentation*.

### 6.1.1 Spazio Libero Minimo su Disco

Per creare un'immagine come `core-image-sato` per la macchina `qemux86-64`, è necessario un sistema con almeno 140 GB di spazio libero su disco. Tuttavia, sarà necessario molto più spazio su disco per creare immagini più complesse, per eseguire più build e per memorizzare nella cache gli artefatti di build, migliorando l'efficienza del processo.

Se lo spazio su disco è insufficiente, consultare la sezione "*Conserving Disk Space*" del Manuale dei Task di Sviluppo.

### 6.1.2 RAM Minima di Sistema

Sarà possibile creare un'immagine come `core-image-sato` per la macchina `qemux86-64` con soli 32 GB di RAM su un vecchio sistema con 4 core CPU, ma le build saranno molto più veloci su un sistema con la massima quantità di RAM e il maggior numero possibile di core CPU.

### 6.1.3 Distribuzioni Linux Supportate

Attualmente, la versione 6.1 ("Blacksail") di Yocto Project è supportata dalle seguenti distribuzioni:

- AlmaLinux 8
- AlmaLinux 9
- AlmaLinux 10
- CentOS Stream 9
- CentOS Stream 10
- Debian 11
- Debian 12
- Debian 13
- Fedora 42
- Fedora 43
- Fedora 44
- openSUSE Leap 15.6
- openSUSE Leap 16.0
- Rocky Linux 8
- Rocky Linux 9
- Rocky Linux 10
- Ubuntu 22.04 (LTS)

- Ubuntu 24.04 (LTS)
- Ubuntu 25.04
- Ubuntu 25.10
- Ubuntu 26.04 (LTS)

Le seguenti versioni di distribuzione sono ancora testate, anche se le organizzazioni che le pubblicano non rendono più disponibili gli aggiornamenti pubblicamente:

- Fedora 42
- openSUSE Leap 15.5
- Ubuntu 25.04
- Ubuntu 25.10

Si noti che Yocto Project non ha accesso agli aggiornamenti privati che alcune di queste versioni potrebbero avere. Pertanto, i nostri test hanno un valore limitato se si ha accesso a tali aggiornamenti. Inoltre, potrebbe essere necessario utilizzare *buildtools* sulle versioni precedenti per ottenere strumenti sufficientemente aggiornati, come Python.

Infine, ecco le versioni di distribuzione che in precedenza venivano testate sulle revisioni precedenti di "Blacksail", ma che ora non lo sono più:

*Questo elenco è attualmente vuoto*

#### Nota

- Sebbene il team di Yocto Project si impegni a garantire la piena compatibilità di tutte le release con ogni distribuzione Linux ufficialmente supportata, è possibile che si verifichino problemi specifici di una determinata distribuzione.
- Le release di Yocto Project vengono testate sulle distribuzioni Linux stabili elencate sopra. Yocto Project dovrebbe funzionare anche su altre distribuzioni, ma non vengono eseguite validazioni su di esse.
- In particolare, Yocto Project non supporta e al momento non prevede di supportare distribuzioni "rolling release" o di sviluppo, data la loro natura in continua evoluzione. Accogliamo con favore patch e segnalazioni di bug, ma si tenga presente che la nostra priorità è rappresentata dalle piattaforme supportate elencate sopra.
- Se la propria distribuzione Linux non è presente nell'elenco, consigliamo di scaricare i tarball *buildtools* o *buildtools-extended* contenenti gli strumenti host richiesti dalla release di Yocto Project, in genere eseguendo `scripts/install-buildtools` come spiegato nella sezione "*Versioni richieste di Git, tar, Python, make e gcc*".
- È possibile utilizzare Windows Subsystem for Linux v2 per configurare un host di build con Windows 10 o versioni successive, oppure Windows Server 2019 o versioni successive, ma la convalida non viene eseguita sugli host di build che utilizzano WSL 2.

Per ulteriori informazioni, consultare la sezione *Setting Up to Use Windows Subsystem For Linux (WSL 2)* nel Manuale di Sviluppo dei Task di Yocto Project.

- In caso di problemi, si prega di visitare [Yocto Project Bugzilla](#) e segnalare un bug. Siamo interessati a conoscere la vostra esperienza. Per informazioni su come segnalare un bug, consultare la pagina wiki di Yocto Project [Bugzilla wiki page](#) e la sezione "*Segnalazione di un Difetto in Yocto Project e in OpenEmbedded*" nella Guida per i Collaboratori di Yocto Project e di OpenEmbedded.

### 6.1.4 Pacchetti Richiesti per l'Host di Build

L'elenco dei pacchetti necessari sul sistema di sviluppo host può essere lungo quando si considerano tutti gli scenari di compilazione con Yocto Project. Questa sezione descrive i pacchetti richiesti in base alla distribuzione Linux e alla funzione.

#### Ubuntu e Debian

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione Linux Ubuntu o Debian supportata:

```
sudo apt-get install build-essential chrpath cpio debianutils diffstat file gawk ↵
↵gcc git iputils-ping libacl1 libcrypt-dev locales python3 python3-git python3-
↵jinja2 python3-pexpect python3-pip python3-subunit socat texinfo unzip wget xz-
↵utils zstd
```

È inoltre necessario assicurarsi che sia abilitata la localizzazione `en_US.UTF-8`:

```
$ locale --all-locales | grep en_US.utf8
```

In caso contrario, è possibile riconfigurare il pacchetto `locales` per aggiungerla (richiede una shell interattiva):

```
$ sudo dpkg-reconfigure locales
```

#### Nota

- Se non si utilizza una shell interattiva, `dpkg-reconfigure` non funzionerà come previsto. Per aggiungere la localizzazione, è necessario modificare il file `/etc/locale.gen` per aggiungere/decommentare la localizzazione `en_US.UTF-8`. Un modo semplice per farlo come root è il seguente:

```
$ echo "en_US.UTF-8 UTF-8" >> /etc/locale.gen
$ locale-gen
```

- Se il sistema di build ha installato il pacchetto `oss4-dev`, si potrebbero riscontrare errori di compilazione di QEMU a causa dell'installazione, da parte del pacchetto, di una propria versione personalizzata di `/usr/include/linux/soundcard.h` sul sistema Debian. Se ci si imbatte in questa situazione, provare una di queste soluzioni:

```
$ sudo apt build-dep qemu
$ sudo apt remove oss4-dev
```



Inoltre, su distribuzioni diverse da Debian 11 e Ubuntu 22.04 (altrimenti vedere la nota seguente), installare il seguente pacchetto:

```
$ sudo apt-get install python3-websockets
```

### **Nota**

Su Debian 11 e Ubuntu 22.04, la versione minima di `python3-websockets` non è soddisfatta dalla distribuzione host. Questo pacchetto viene utilizzato per scaricare gli artefatti *shared state* precompilati dai server di Yocto Project (vedere *core/yocto/sstate-mirror-cdn* per maggiori informazioni).

Per utilizzare questa funzionalità, si può ottenere la versione corretta di `python3-websockets` in uno dei seguenti modi:

- Utilizzando un tarball *buildtools* seguendo la sezione *Versioni richieste di Git, tar, Python, make e gcc* qui di seguito.
- Installazione di `python3-websockets` tramite *Pip* in un ambiente virtuale, ad esempio:

```
$ python3 -m venv --clear ./yocto-docs-venv
$ . ./yocto-docs-venv/bin/activate
$ pip install websockets
```

Ecco i pacchetti necessari per creare i manuali di documentazione del Progetto:

```
sudo apt install git librsvg2-bin locales make python3-pip python3-venv
```

```
python3 -m venv --clear ./yocto-docs-venv
. ./yocto-docs-venv/bin/activate
python3 -m pip install sphinx sphinx_rtd_theme pyyaml sphinx-copybutton
↪ 'sphinxcontrib-svg2pdfconverter>=2.0.0'
```

Oltre ai pacchetti precedenti, ecco quelli necessari per creare la documentazione in formato PDF:

```
sudo apt install fonts-freefont-otf latexmk tex-gyre texlive-fonts-extra texlive-
↪ fonts-recommended texlive-lang-all texlive-latex-extra texlive-latex-recommended
↪ texlive-xetex
```

## **Pacchetti Fedora**

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione Fedora Linux supportata:

```
sudo dnf install bzip2 chrpath cpio cpp diffstat diffutils file findutils gawk gcc
↪ gcc-c++ git glibc-devel glibc-langpack-en gzip hostname libacl make patch perl
↪ perl-Data-Dumper perl-File-Compare perl-File-Copy perl-FindBin perl-Text-
↪ ParseWords perl-Thread-Queue perl-bignum perl-locale python python3 python3-
```

(continues on next page)

(continua dalla pagina precedente)

```
↪GitPython python3-jinja2 python3-pexpect python3-pip python3-websockets rpcgen↵
↪socat tar texinfo unzip wget which xz zstd $([ $(rpm -E %fedora) -ge 42 ] &&↵
↪echo "util-linux-script")
```

Ecco i pacchetti necessari per creare i manuali di documentazione del Progetto:

```
sudo dnf install git glibc-locale-source librsvg2-tools make python3-pip which
```

```
python3 -m venv --clear ./yocto-docs-venv
. ./yocto-docs-venv/bin/activate
python3 -m pip install sphinx sphinx_rtd_theme pyyaml sphinx-copybutton
↪'sphinxcontrib-svg2pdfconverter>=2.0.0'
```

Oltre ai pacchetti precedenti, ecco quelli necessari per creare la documentazione in formato PDF:

```
sudo dnf install 'texlive-collection-lang*' latexmk texlive-collection-fontsextra↵
↪texlive-collection-fontsrecommended texlive-collection-latex texlive-collection-
↪latexextra texlive-collection-latexrecommended texlive-collection-xetex texlive-
↪fncychap texlive-gnu-freefont texlive-tex-gyre texlive-xetex
```

## Pacchetti openSUSE Leap

### Pacchetti openSUSE Leap 15.6

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione openSUSE Leap 15.6 supportata:

```
sudo zypper install bzip2 chrpath diffstat gcc gcc-c++ git gzip hostname libacl1↵
↪make makeinfo patch python python-curses python-xml python3 python3-Jinja2↵
↪python3-curses python3-pexpect python3-pip rpcgen socat tar wget which xz zstd
sudo pip3 install GitPython
```

Inoltre, openSUSE Leap 15.6 richiede l'installazione e la configurazione di un tarball di *buildtools*, poiché questa distribuzione fornisce una versione di Python troppo vecchia per *BitBake*. Per ulteriori informazioni, consultare la sezione *Versioni richieste di Git, tar, Python, make e gcc* riportata di seguito.

Ecco i pacchetti necessari per creare i manuali di documentazione del Progetto:

```
sudo zypper install git glibc-i18ndata make python3-pip rsvg-convert which
```

```
python3 -m venv --clear ./yocto-docs-venv
. ./yocto-docs-venv/bin/activate
python3 -m pip install sphinx sphinx_rtd_theme pyyaml sphinx-copybutton
↪'sphinxcontrib-svg2pdfconverter>=2.0.0'
```

Oltre ai pacchetti precedenti, ecco quelli necessari per creare la documentazione in formato PDF:

```
sudo zypper install 'texlive-collection-lang*' texlive-collection-fontsextra_
↳texlive-collection-fontsrecommended texlive-collection-latex texlive-collection-
↳latexextra texlive-collection-latexrecommended texlive-collection-xetex texlive-
↳fncychap texlive-gnu-freefont texlive-latexmk texlive-tex-gyre texlive-xetex
```

## Pacchetti openSUSE Leap 16.0

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione openSUSE Leap 16.0 supportata:

```
sudo zypper install bzip2 chrpath diffstat gcc gcc-c++ git gzip hostname libacl1_
↳make makeinfo patch python3 python3-GitPython python3-Jinja2 python3-curses_
↳python3-pexpect python3-pip python3-websockets python3-xml rpcgen socat tar wget_
↳which xz zstd
```

Ecco i pacchetti necessari per creare i manuali di documentazione del Progetto:

```
sudo zypper install git glibc-i18ndata make python3-pip rsvg-convert which
```

```
python3 -m venv --clear ./yocto-docs-venv
. ./yocto-docs-venv/bin/activate
python3 -m pip install sphinx sphinx_rtd_theme pyyaml sphinx-copybutton
↳'sphinxcontrib-svg2pdfconverter>=2.0.0'
```

Oltre ai pacchetti precedenti, ecco quelli necessari per creare la documentazione in formato PDF:

```
sudo zypper install 'texlive-collection-lang*' texlive-collection-fontsextra_
↳texlive-collection-fontsrecommended texlive-collection-latex texlive-collection-
↳latexextra texlive-collection-latexrecommended texlive-collection-xetex texlive-
↳fncychap texlive-gnu-freefont texlive-latexmk texlive-tex-gyre texlive-xetex
```

## Pacchetti AlmaLinux

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione AlmaLinux supportata:

```
sudo dnf install -y epel-release
sudo dnf install -y dnf-plugins-core
sudo dnf config-manager --set-enabled crb || sudo dnf config-manager --set-enabled_
↳powertools
sudo dnf makecache
sudo dnf install -y bzip2 chrpath cpio cpp diffstat diffutils gawk gcc gcc-c++ git_
↳glibc-devel glibc-langpack-en gzip libacl make patch perl perl-Data-Dumper perl-
↳Text-ParseWords perl-Thread-Queue python3 python3-GitPython python3-jinja2_
↳python3-pexpect python3-pip rpcgen socat tar texinfo unzip wget which xz zstd
```

Sarà inoltre necessario utilizzare un file tarball *buildtools* che fornisce una serie di strumenti host di base con versioni fisse. Seguire la sezione *Versioni richieste di Git, tar, Python, make e gcc* di seguito per scoprire come scaricare e installare questo file tarball.

#### Nota

Le distribuzioni AlmaLinux 9, CentOS 9 e RockyLinux 9 sono interessate da un bug descritto in [https://bugzilla.yoctoproject.org/show\\_bug.cgi?id=16143](https://bugzilla.yoctoproject.org/show_bug.cgi?id=16143), motivo per cui è necessario un file tarball *buildtools*.

#### Nota

- Extra Packages for Enterprise Linux (ovvero *epel-release*) è una raccolta di pacchetti di Fedora basati su RHEL/CentOS per facilitare l'installazione di pacchetti non inclusi di default in Enterprise Linux. È necessario installare questi pacchetti separatamente.
- Il repository *PowerTools/CRB* fornisce pacchetti aggiuntivi come *rpcgen* e *texinfo*.
- Il comando *makecache* utilizza Metadati aggiuntivi da *epel-release*.

Ecco i pacchetti necessari per creare i manuali di documentazione del Progetto:

```
sudo dnf install -y git glibc-locale-source librsvg2-tools make python3-pip which
```

```
python3 -m venv --clear ./yocto-docs-venv
. ./yocto-docs-venv/bin/activate
python3 -m pip install sphinx sphinx_rtd_theme pyyaml sphinx-copybutton
↪ 'sphinxcontrib-svg2pdfconverter>=2.0.0'
```

Oltre ai pacchetti precedenti, per creare la documentazione in formato PDF sono necessari i seguenti pacchetti TeX Live, installabili tramite il [gestore di pacchetti TeX Live](#):

```
sudo dnf install -y wget perl
textooldir=${TEXTTOOLDIR:-"./docs-build-tex-tools"}
mkdir -p "$textooldir"/tl
wget https://mirror.ctan.org/systems/texlive/tlnet/install-tl-unx.tar.gz -O "
↪$textooldir"/install-tl-unx.tar.gz
tar xzf "$textooldir"/install-tl-unx.tar.gz -C "$textooldir"
"$textooldir"/install-tl-*/install-tl --scheme=small --texdir="$textooldir"/tl --
↪no-interaction
PATH="$PATH:$textooldir/tl/bin/x86_64-linux" tlmgr install titlesec varwidth_
↪tabulary needspace upquote framed capt-of wrapfig fncychap gnu-freefont ctex_
↪latexmk nimbus15
rm -r "$textooldir"/install-tl*
```

**⚠ Avvertimento**

L'installazione di TeX Live sopra descritta è valida solo per sistemi host *x86\_64*.

Prima di creare la documentazione in PDF, impostare la variabile d'ambiente `PATH` per utilizzare i pacchetti installati (con `${textoolldir}` che punta all'installazione di TeX Live del passaggio precedente):

```
$ export PATH="${PATH}:${textoolldir}/tl/bin/x86_64-linux"
```

**Pacchetti CentOS Stream**

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione CentOS Stream supportata:

```
sudo dnf install -y epel-release
sudo dnf install -y dnf-plugins-core
sudo dnf config-manager --set-enabled crb || sudo dnf config-manager --set-enabled_
↳powertools
sudo dnf makecache
sudo dnf install -y bzip2 chrpath cpio cpp diffstat diffutils gawk gcc gcc-c++ git_
↳glibc-devel glibc-langpack-en gzip libacl make patch perl perl-Data-Dumper perl-
↳Text-ParseWords perl-Thread-Queue python3 python3-GitPython python3-jinja2_
↳python3-pexpect python3-pip rpcgen socat tar texinfo unzip wget which xz zstd
```

Sarà inoltre necessario utilizzare un file tarball *buildtools* che fornisce una serie di strumenti host di base con versioni fisse. Seguire la sezione *Versioni richieste di Git, tar, Python, make e gcc* di seguito per scoprire come scaricare e installare questo file tarball.

**i Nota**

Le distribuzioni AlmaLinux 9, CentOS 9 e RockyLinux 9 sono interessate da un bug descritto in [https://bugzilla.yoctoproject.org/show\\_bug.cgi?id=16143](https://bugzilla.yoctoproject.org/show_bug.cgi?id=16143), motivo per cui è necessario un file tarball *buildtools*.

Ecco i pacchetti necessari per creare i manuali di documentazione del Progetto:

```
sudo dnf install -y git glibc-locale-source librsvg2-tools make python3-pip which
```

```
python3 -m venv --clear ./yocto-docs-venv
. ./yocto-docs-venv/bin/activate
python3 -m pip install sphinx sphinx_rtd_theme pyyaml sphinx-copybutton
↳'sphinxcontrib-svg2pdfconverter>=2.0.0'
```

Oltre ai pacchetti precedenti, per creare la documentazione in formato PDF sono necessari i seguenti pacchetti TeX Live, installabili tramite il [gestore di pacchetti TeX Live](#):

```

sudo dnf install -y wget perl
textooldir=${TEXTTOOLDIR:-"./docs-build-tex-tools"}
mkdir -p "$textooldir"/tl
wget https://mirror.ctan.org/systems/texlive/tlnet/install-tl-unx.tar.gz -O "
↪$textooldir"/install-tl-unx.tar.gz
tar xzf "$textooldir"/install-tl-unx.tar.gz -C "$textooldir"
"$textooldir"/install-tl-*/install-tl --scheme=small --texdir="$textooldir"/tl --
↪no-interaction
PATH="$PATH:$textooldir/tl/bin/x86_64-linux" tlmgr install titlesec varwidth_
↪tabulary needspace upquote framed capt-of wrapfig fncychap gnu-freefont ctex_
↪latexmk nimbus15
rm -r "$textooldir"/install-tl*

```

### ⚠ Avvertimento

L'installazione di TeX Live sopra descritta è valida solo per sistemi host `x86_64`.

Prima di creare la documentazione in PDF, impostare la variabile d'ambiente `PATH` per utilizzare i pacchetti installati (con `$textooldir` che punta all'installazione di TeX Live del passaggio precedente):

```
$ export PATH="$PATH:$textooldir/tl/bin/x86_64-linux"
```

## Pacchetti RockyLinux

Ecco i pacchetti necessari per creare un'immagine su un sistema senza interfaccia grafica con una distribuzione RockyLinux supportata:

```

sudo dnf install -y epel-release
sudo dnf install -y dnf-plugins-core
sudo dnf config-manager --set-enabled crb || sudo dnf config-manager --set-enabled_
↪powertools
sudo dnf makecache
sudo dnf install -y bzip2 chrpath cpio cpp diffstat diffutils gawk gcc gcc-c++ git_
↪glibc-devel glibc-langpack-en gzip libacl make patch perl perl-Data-Dumper perl-
↪Text-ParseWords perl-Thread-Queue python3 python3-GitPython python3-jinja2_
↪python3-pexpect python3-pip rpcgen socat tar texinfo unzip wget which xz zstd

```

Sarà inoltre necessario utilizzare un file tarball *buildtools* che fornisce una serie di strumenti host di base con versioni fisse. Seguire la sezione *Versioni richieste di Git, tar, Python, make e gcc* di seguito per scoprire come scaricare e installare questo file tarball.

**i Nota**

Le distribuzioni AlmaLinux 9, CentOS 9 e RockyLinux 9 sono interessate da un bug descritto in [https://bugzilla.yoctoproject.org/show\\_bug.cgi?id=16143](https://bugzilla.yoctoproject.org/show_bug.cgi?id=16143), motivo per cui è necessario un file tarball *buildtools*.

**i Nota**

- Extra Packages for Enterprise Linux (ovvero *epel-release*) è una raccolta di pacchetti di Fedora basati su RHEL/CentOS per facilitare l'installazione di pacchetti non inclusi di default in Enterprise Linux. È necessario installare questi pacchetti separatamente.
- Il repository *PowerTools/CRB* fornisce pacchetti aggiuntivi come *rpcgen* e *texinfo*.
- Il comando *makecache* utilizza Metadati aggiuntivi da *epel-release*.

Ecco i pacchetti necessari per creare i manuali di documentazione del Progetto:

```
sudo dnf install -y git glibc-locale-source librsvg2-tools make python3-pip which
```

```
python3 -m venv --clear ./yocto-docs-venv
. ./yocto-docs-venv/bin/activate
python3 -m pip install sphinx sphinx_rtd_theme pyyaml sphinx-copybutton
↪ 'sphinxcontrib-svg2pdfconverter>=2.0.0'
```

Oltre ai pacchetti precedenti, per creare la documentazione in formato PDF sono necessari i seguenti pacchetti TeX Live, installabili tramite il [gestore di pacchetti TeX Live](#):

```
sudo dnf install -y wget perl
textooldir=${TEXTTOOLDIR:-"./docs-build-tex-tools"}
mkdir -p "$textooldir"/tl
wget https://mirror.ctan.org/systems/texlive/tlnet/install-tl-unx.tar.gz -O "
↪ $textooldir/install-tl-unx.tar.gz
tar xzf "$textooldir/install-tl-unx.tar.gz" -C "$textooldir"
"$textooldir/install-tl-*/install-tl --scheme=small --texdir="$textooldir"/tl --
↪ no-interaction
PATH="$PATH:$textooldir/tl/bin/x86_64-linux" tlmgr install titlesec varwidth_
↪ tabulary needspace upquote framed capt-of wrapfig fncychap gnu-freefont ctex_
↪ latexmk nimbus15
rm -r "$textooldir/install-tl*
```

**⚠ Avvertimento**

L'installazione di TeX Live sopra descritta è valida solo per sistemi host *x86\_64*.

Prima di creare la documentazione in PDF, impostare la variabile d'ambiente `PATH` per utilizzare i pacchetti installati (con `${textooldir}` che punta all'installazione di TeX Live del passaggio precedente):

```
$ export PATH="${PATH}:${textooldir}/tl/bin/x86_64-linux"
```

## 6.1.5 Versioni richieste di Git, tar, Python, make e gcc

Per utilizzare il sistema di build, il sistema host di sviluppo deve soddisfare i seguenti requisiti di versione per Git, tar e Python:

- Git 2.22.0 o superiore
- tar 1.28 o superiore
- Python 3.9.0 o superiore
- GNU make 4.0 o superiore

Se il sistema host di sviluppo non soddisfa tutti questi requisiti, è possibile risolvere il problema installando un file tarball *buildtools* contenente questi strumenti. È possibile scaricare un file tarball precompilato oppure utilizzare BitBake per crearne uno.

Inoltre, il sistema host di sviluppo deve soddisfare il seguente requisito di versione per gcc:

- gcc 10.1 o superiore

Se il sistema host di sviluppo non soddisfa questo requisito, è possibile risolvere il problema installando un tarball *buildtools-extended* che contiene strumenti aggiuntivi, l'equivalente del pacchetto `build-essential` di Debian/Ubuntu.

Per i sistemi con una versione di make non funzionante (ad esempio make 4.2.1 senza patch) ma in cui gli altri strumenti host sono utilizzabili, è possibile utilizzare il tarball *buildtools-make*.

Nelle sezioni seguenti, verranno descritti tre diversi metodi per installare i toolset *buildtools*, *buildtools-extended* o *buildtools-make*.

### Installazione di un tarball *buildtools* Pre-Built con lo script `install-buildtools`

Lo script `install-buildtools` è il più semplice dei tre metodi per ottenere questi strumenti. Scaricare un programma di installazione precompilato di *buildtools* e installare automaticamente gli strumenti:

1. Eseguire lo script `install-buildtools`. Ecco un esempio:

```
$ cd /path/to/bitbake-builds
$ ./layers/openembedded-core/scripts/install-buildtools \
  --without-extended-buildtools \
  --base-url https://downloads.yoctoproject.org/releases/yocto \
```

(continues on next page)



(continua dalla pagina precedente)

```
--release yocto-6.1 \  
--installer-version 6.1
```

Durante l'esecuzione, verrà scaricato il file tarball di *buildtools*, verrà verificato il checksum del download, verrà eseguito il programma di installazione e verranno effettuati alcuni controlli di base per assicurarsi che l'installazione sia funzionante.

Per evitare la necessità di privilegi `sudo`, lo script `install-buildtools`, per default, indicherà al programma di installazione di installare i pacchetti nella directory:

```
/path/to/bitbake-builds/buildtools
```

Se il sistema host di sviluppo necessita degli strumenti aggiuntivi forniti nel file tarball *buildtools-extended*, è possibile eseguire lo script `install-buildtools` con i parametri di default:

```
$ cd /path/to/bitbake-builds  
$ ./layers/openembedded-core/scripts/install-buildtools
```

In alternativa, se il sistema host di sviluppo ha una versione di `make` non funzionante e si necessita solo di una versione funzionante, è possibile utilizzare l'opzione `--make-only`:

```
$ cd /path/to/bitbake-builds  
$ ./layers/openembedded-core/scripts/install-buildtools --make-only
```

2. Eseguire lo script di configurazione dell'ambiente degli strumenti utilizzando un comando simile al seguente:

```
$ source /path/to/bitbake-builds/buildtools/environment-setup-x86_64-pokysdk-  
↪ linux
```

Dopo aver eseguito lo script di configurazione, gli strumenti vengono aggiunti a `PATH` e vengono inizializzate tutte le altre variabili d'ambiente necessarie per il loro funzionamento. Il risultato saranno versioni funzionanti di `Git`, `tar`, `Python` e `chrpath`. E nel caso del tarball *buildtools-extended*, sono presenti versioni funzionanti aggiuntive di strumenti tra cui `gcc`, `make` e gli altri strumenti inclusi in `packagegroup-core-buildessential`.

## Download di un Archivio Tarball Precompilato di *buildtools*

Se si preferisce non utilizzare lo script `install-buildtools`, si può scaricare ed eseguire autonomamente un programma di installazione precompilato di *buildtools* seguendo questi passaggi:

1. Recarsi nella directory [https://downloads.yoctoproject.org/releases/yocto/yocto-6.1\\_M3/buildtools/](https://downloads.yoctoproject.org/releases/yocto/yocto-6.1_M3/buildtools/), individuare e scaricare il file `.sh` corrispondente all'architettura del proprio sistema host e a *buildtools*, *buildtools-extended* o *buildtools-make*.
2. Eseguire lo script di installazione. Ecco un esempio per il programma di installazione tradizionale:

```
$ sh ~/Downloads/x86_64-buildtools-nativesdk-standalone-6.1.sh
```

Ecco un esempio per il programma di installazione esteso:

```
$ sh ~/Downloads/x86_64-buildtools-extended-nativesdk-standalone-6.1.sh
```

Esempio per il programma di installazione solo make:

```
$ sh ~/Downloads/x86_64-buildtools-make-nativesdk-standalone-6.1.sh
```

Durante l'esecuzione, verrà visualizzato un prompt che permetterà di scegliere la directory di installazione. Ad esempio, si potrebbe scegliere il seguente path: `/home/your-username/buildtools`

3. Come indicato dallo script di installazione, dovrai eseguire lo script di configurazione dell'ambiente degli strumenti:

```
$ source /home/your_username/buildtools/environment-setup-x86_64-pokysdk-linux
```

Dopo aver eseguito lo script di configurazione, gli strumenti vengono aggiunti a `PATH` e vengono inizializzate tutte le altre variabili d'ambiente necessarie per il loro funzionamento. Il risultato saranno versioni funzionanti di Git, tar, Python e `chrpath`. E nel caso del tarball *buildtools-extended*, sono presenti versioni funzionanti aggiuntive di strumenti tra cui `gcc`, `make` e gli altri strumenti inclusi in `packagegroup-core-buildessential`.

## Building del Proprio Archivio tar di *buildtools*

La creazione e l'esecuzione del proprio programma di installazione di *buildtools* è possibile solo se si dispone di un host di build in grado di eseguire BitBake. In questo caso, si utilizza tale macchina per creare il file `.sh` e quindi si procede al trasferimento e all'esecuzione su una macchina che non soddisfa i requisiti minimi di Git, tar e Python (o `gcc`).

Ecco i passaggi da seguire per creare ed eseguire il proprio programma di installazione di *buildtools*:

1. Sulla macchina in grado di eseguire BitBake, assicurarsi di aver configurato l'ambiente di build con lo script di configurazione (*oe-init-build-env*).
2. Eseguire il comando BitBake per creare il tarball:

```
$ bitbake buildtools-tarball
```

oppure per creare il tarball esteso:

```
$ bitbake buildtools-extended-tarball
```

oppure per creare il tarball con `soll` make:

```
$ bitbake buildtools-make-tarball
```

**Nota**

La variabile *SDKMACHINE* determina se si compilano gli strumenti per un sistema a 32 bit o a 64 bit.

Una volta completata la compilazione, è possibile trovare il file `.sh` che installa gli strumenti nella sottocartella `tmp/deploy/sdk` della directory di *Build Directory*. Il file di installazione ha la stringa "buildtools" o "buildtools-extended" nel nome.

- Trasferire il file `.sh` dall'host di compilazione alla macchina che non soddisfa i requisiti di Git, tar o Python (o gcc).
- Su questa macchina, si esegue il file `.sh` per installare gli strumenti. Ecco un esempio per l'installazione tradizionale:

```
$ sh ~/Downloads/x86_64-buildtools-nativesdk-standalone-6.1.sh
```

Per l'installazione estesa:

```
$ sh ~/Downloads/x86_64-buildtools-extended-nativesdk-standalone-6.1.sh
```

E per l'installazione solo con make:

```
$ sh ~/Downloads/x86_64-buildtools-make-nativesdk-standalone-6.1.sh
```

Durante l'esecuzione, verrà visualizzato un prompt che consente di scegliere la directory di installazione. Ad esempio, è possibile scegliere la seguente: `/home/your_username/buildtools`

- Eseguire lo script di configurazione dell'ambiente degli strumenti utilizzando un comando simile al seguente:

```
$ source /home/your_username/buildtools/environment-setup-x86_64-poky-linux
```

Dopo aver eseguito lo script di configurazione, gli strumenti vengono aggiunti a `PATH` e vengono inizializzate tutte le altre variabili d'ambiente necessarie per il loro funzionamento. Il risultato saranno versioni funzionanti di Git, tar, Python e `chrpath`. E nel caso del tarball *buildtools-extended*, sono presenti versioni funzionanti aggiuntive di strumenti tra cui `gcc`, `make` e gli altri strumenti inclusi in `packagegroup-core-buildessential`.

## 6.2 Architetture e Funzionalità Supportate da Yocto Project

Yocto Project si impegna costantemente a testare le modifiche apportate ai metadati e agli strumenti principali di *OpenEmbedded-Core (OE-Core)*. I dettagli sul funzionamento di questo ambiente di test sono descritti nel *Manuale dell'Ambiente di Test di Yocto Project*.

Questi test vengono eseguiti anche per le versioni stabili e *LTS* di Yocto Project. Per ulteriori informazioni su queste tipologie di rilascio, consultare la sezione *Rilasci di Yocto Project e Iter dei Rilasci Stabili* del Manuale di Riferimento di Yocto Project.

L'infrastruttura alla base dell'ambiente di test è *Yocto Project Autobuilder*. L'Autobuilder contiene una serie di Builder associati a un'architettura o a una funzionalità da testare. Ad esempio, il builder `qemuarm64` corrisponde al test dell'architettura ARM a 64 bit.

Di seguito è riportato un elenco completo delle architetture target e delle funzionalità supportate, nonché il relativo livello di supporto. Per ogni architettura o funzionalità, sono elencati anche i relativi sviluppatori.

### 6.2.1 Supporto Primario

Il termine "primario" indica che per queste architetture o funzionalità vengono eseguite quotidianamente build dedicate sull'Autobuilder di Yocto Project e che queste vengono testate con le modifiche in arrivo prima di essere integrate. Tali modifiche si trovano solitamente sui branch Git "-next" dei repository *OpenEmbedded-Core (OE-Core)*.

Di seguito è riportato un elenco delle funzionalità principali testate, con i relativi manutentori e sviluppatori:

| Funzionalità               | Descrizione                                                                                                                                                            | Manutentori                                                 | Builder                                                                                                                                                                                                |
|----------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ARM                        | Test dell'architettura ARM                                                                                                                                             | Sforzo collettivo                                           | genericarm64, genericarm64-alt, musl-qemuarm64, qemuarm, qemuarm-alt, qemuarm-oecore, qemuarm-tc, qemuarm64, qemuarm64-alt, qemuarm64-armhost, qemuarm64-ltp, qemuarm64-ptest, qemuarm64-tc, qemuarmv5 |
| Beaglebone                 | Test dell'immagine Beaglebone e della build SDK                                                                                                                        | Sforzo collettivo                                           | beaglebone, beaglebone-alt                                                                                                                                                                             |
| Riproducibile              | Test di riproducibilità                                                                                                                                                | Sforzo collettivo                                           | reproducible                                                                                                                                                                                           |
| Buildtools                 | Generazione di buildtools                                                                                                                                              | Sforzo collettivo                                           | buildtools                                                                                                                                                                                             |
| meta-agl-core              | Test del layer meta-agl-core                                                                                                                                           | TBD                                                         | meta-agl-core                                                                                                                                                                                          |
| meta-arm                   | Test del layer meta-arm                                                                                                                                                | meta-arm mailing list <meta-arm@lists.yoctoproject.org>     | meta-arm                                                                                                                                                                                               |
| meta-aws                   | Test del layer meta-aws                                                                                                                                                | TBD                                                         | meta-aws                                                                                                                                                                                               |
| meta-intel                 | Test del layer meta-intel                                                                                                                                              | meta-intel mailing list <meta-intel@lists.yoctoproject.org> | meta-intel                                                                                                                                                                                             |
| meta-exein                 | Test del layer meta-exein                                                                                                                                              | TBD                                                         | meta-exein                                                                                                                                                                                             |
| meta-webosose              | Test del layer meta-webosose                                                                                                                                           | TBD                                                         | meta-webosose                                                                                                                                                                                          |
| Multilib                   | Test delle funzionalità di Multilib                                                                                                                                    | Sforzo collettivo                                           | multilib                                                                                                                                                                                               |
| OpenEmbedded-Core selftest | Auto-test dei layer di OpenEmbedded-Core                                                                                                                               | Sforzo collettivo                                           | oe-selftest-fedora, oe-selftest-debian, oe-selftest-armhost                                                                                                                                            |
| Gestori di pacchetti       | Test dei gestori di pacchetti (formati RPM, DEB e IPK) in <i>OpenEmbedded Build System</i> (diverso dalla funzionalità <code>package-management image feature</code> ) | Sforzo collettivo                                           | pkgman-non-rpm (altri builder utilizzano RPM per default)                                                                                                                                              |
| Patchtest                  | Auto-test del tool Patchtest                                                                                                                                           | Sforzo collettivo                                           | patchtest-selftest                                                                                                                                                                                     |
| RISC-V (64-bit)            | Test                                                                                                                                                                   | Sforzo collettivo                                           | qemuriscv64, qemuriscv64-ptest, qemuriscv64-tc                                                                                                                                                         |
| systemd                    | Test del gestore di                                                                                                                                                    | Sforzo collettivo                                           | no-x11, qa-extras2                                                                                                                                                                                     |

## 6.2.2 Supporto Secondario

Il termine "secondario" indica che, in alcuni casi, esiste del codice/funzionalità/supporto desiderato dagli utenti del progetto e che è nell'interesse del progetto stesso supportare, tuttavia non vi è un interesse e un supporto sufficientemente ampi da giustificare il test di tutte le modifiche in arrivo. Esistono comunque organizzazioni membri del progetto e manutentori disposti a eseguire test e revisionare le correzioni.

Questa categoria può essere applicabile quando il supporto/l'utilizzo in un'area si sviluppa e cresce, oppure quando il supporto/l'utilizzo diminuisce ma continuiamo ad avere test. Può anche essere applicabile quando non sono disponibili risorse per un supporto primario completo, ma vi è il supporto di membri/manutentori per l'esecuzione dei test.

Pertanto, abbiamo i seguenti criteri e politiche per tali elementi:

- Può essere chiaramente isolato e definito da una configurazione specifica.
- Esiste un gruppo chiaramente documentato di manutentori che si impegnano a mantenerlo.
- Tali manutentori sono attivi e "responsive" [reattivi].
- È in fase di test attivo e pubblico (potenzialmente utilizzando l'*Autobuilder* previo accordo, o in altro modo).
- I test non faranno parte dei test standard delle modifiche in entrata e le regressioni non bloccheranno le patch in arrivo.
- Il team *SWAT* non gestirà alcuna build di test sull'*Autobuilder*.
- I risultati dei test possono essere inviati come parte del processo di rilascio, se lo si desidera.

Il *Technical Steering Committee (TSC)* di Yocto Project prende le decisioni sulle funzionalità in questo stato e sui test dell'*Autobuilder*. Tale supporto verrebbe interrotto se i manutentori/tester fossero inattivi.

Se si è interessati a fornire risorse per migliorare i test, contattare il *Technical Steering Committee (TSC)*.

Di seguito è riportato un elenco delle funzionalità secondarie testate, con i relativi manutentori e sviluppatori:

| Funzionalità        | Descrizione                             | Manutentori                                                                                 | Builder                                  |
|---------------------|-----------------------------------------|---------------------------------------------------------------------------------------------|------------------------------------------|
| PowerPC (32-bit)    | Test dell'architettura PowerPC (32 bit) | Peter Marko, Adrian Freihofer                                                               | qemuppc, qemuppc-tc                      |
| meta-openembedded   | Test del layer meta-openembedded        | Sforzo collettivo / mailing list di openembedded-devel<br><openembedded-devel@lists.openemb | meta-oe                                  |
| meta-mingw          | Test degli SDK basati su mingw          | TBD                                                                                         | meta-mingw                               |
| meta-virtualization | Test del layer meta-virtualization      | mailing list di meta-virtualization<br><meta-virtualization@lists.y                         | meta-virt                                |
| RISC-V (32-bit)     | Test dell'architettura RISC-V (32 bit)  | TBD                                                                                         | qemuriscv32, qemuriscv32, qemuriscv32-tc |

### 6.2.3 Untested

"Untested" significa che, sebbene le configurazioni siano presenti nel progetto, al momento non eseguiamo i test regolarmente e le nuove modifiche non vengono testate rispetto a queste. Potremmo accettare patch in queste aree se ritenute opportune, ma solo previo impegno.

| Funzionalità             | Descrizione                                         | Manutentori        | Builder                                                        |
|--------------------------|-----------------------------------------------------|--------------------|----------------------------------------------------------------|
| MIPS                     | Test dell'architettura MIPS                         | Nessun manutentore | qemumips, qemumips64, qemumips-alt, qemumips-tc, qemumips64-tc |
| PowerPC (32-bit) Systemd | Test dell'architettura PowerPC (32 bit) con systemd | Nessun manutentore | qemuppc-alt                                                    |
| PowerPC (64-bit)         | Test dell'architettura PowerPC (64 bit)             | Nessun manutentore | qemuppc64, qemuppc64-tc                                        |

## 6.3 Terminologia di Yocto Project

Ecco un elenco di termini e definizioni che potrebbero essere utili agli utenti che si avvicinano per la prima volta all'ambiente di sviluppo del Yocto Project. Sebbene alcuni di questi termini siano universali, l'elenco li include per completezza:

### *File Append*

File che aggiungono informazioni di build a un file di ricetta. I file append sono noti come file append di BitBake e file `.bbappend`. Il sistema di build OpenEmbedded prevede che ogni file append abbia un file di ricetta (`.bb`) corrispondente. Inoltre, il file append e il file ricetta corrispondente devono utilizzare lo stesso nome file radice. I nomi dei file possono differire solo per il suffisso del tipo di file utilizzato (ad esempio, `formfactor_0.0.bb` e `formfactor_0.0.bbappend`).

Le informazioni contenute nei file append estendono o sovrascrivono le informazioni presenti nel file di ricetta con lo stesso nome. Per un esempio di file append in uso, consultare la sezione "[Appending Other Layers Metadata With Your Layer](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

Quando si assegna un nome a un file append, è possibile utilizzare il carattere jolly "%" per consentire la corrispondenza con i nomi delle ricette. Ad esempio, si supponga di avere un file append denominato come segue:

```
busybox_1.21.%.bbappend
```

Questo file append corrisponderà a qualsiasi versione della ricetta `busybox_1.21.x.bb`. Quindi, il file append corrisponderà a uno qualsiasi dei seguenti nomi di ricetta:

```
busybox_1.21.1.bb
busybox_1.21.2.bb
busybox_1.21.3.bb
busybox_1.21.10.bb
busybox_1.21.25.bb
```

### Nota

L'uso del carattere "%" è limitato al fatto che funziona solo direttamente prima della parte `.bbappend` del nome del file di append. Non è possibile utilizzare il carattere jolly in nessun'altra posizione del nome.

### *BitBake*

L'esecutore e lo scheduler di task utilizzati dal sistema di build OpenEmbedded per creare le immagini. Per ulteriori informazioni su BitBake, consultare il [Manuale Utente di BitBake](#).

### *Board Support Package (BSP)*

Un gruppo di driver, definizioni e altri componenti che forniscono supporto per una specifica configurazione hardware. Per ulteriori informazioni sui BSP, consultare il [Manuale del Board Support Package \(BSP\) di Yocto Project](#).

### *Directory di Build*

Questo termine si riferisce all'area utilizzata dal sistema di compilazione OpenEmbedded per le build. L'area



viene creata quando si esegue `source` lo script di configurazione dell'ambiente che si trova nella directory dei sorgenti (ad esempio, `oe-init-build-env` o `init-build-env` quando si utilizza `bitbake-setup`). La variabile `TOPDIR` punta alla *Build Directory*.

Quando si configura la build manualmente (vedere *Setting Up the Poky Reference Distro Manually*), si ha molta flessibilità nella creazione della *Build Directory*. Ecco alcuni esempi che mostrano come creare la directory. Gli esempi presuppongono che la *Source Directory* si chiami `bitbake-builds`:

- Creare la *Build Directory* all'interno della Source Directory e lascia che il nome predefinito della *Build Directory* sia `build`:

```
$ cd bitbake-builds
$ source layers/openembedded-core/oe-init-build-env
```

- In alternativa, specifica il percorso della *Build Directory* quando si esegue `oe-init-build-env`. Tutte le cartelle intermedie nel path devono esistere. L'esempio seguente crea una *Build Directory* denominata `YP-6.1` all'interno della directory esistente `mybuilds`:

```
$ source bitbake-builds/layers/openembedded-core/oe-init-build-env \
↪mybuilds/YP-6.1
```

Questo path può anche essere un percorso assoluto e trovarsi al di fuori della directory di lavoro corrente:

```
$ source bitbake-builds/layers/openembedded-core/oe-init-build-env /opt/
↪mybuilds/YP-6.1
```

#### Nota

Per default, la *Build Directory* contiene `TMPDIR`, una directory temporanea utilizzata dal sistema di compilazione. `TMPDIR` non può trovarsi su un server NFS. Pertanto, per default, la *Build Directory* non può trovarsi su un server NFS. Tuttavia, se è necessario che la *Build Directory* si trovi su NFS, è possibile configurarla impostando `TMPDIR` nel file `build/conf/site.conf` in modo che utilizzi un'unità locale. In questo modo, `TMPDIR` viene effettivamente separato da `TOPDIR`, che rappresenta la *Build Directory*.

### Host di Build

Il sistema utilizzato per creare immagini in un Ambiente di Sviluppo di Yocto Project. Il sistema di compilazione viene talvolta chiamato "Host di Sviluppo" o "Build Host".

#### *buildtools*

Tool di compilazione in formato binario, che forniscono le versioni necessarie degli strumenti di sviluppo (come Git, GCC, Python e make) per eseguire il sistema di build di OpenEmbedded su un host di sviluppo che non dispone di tali versioni minime.

Consultare il paragrafo "*Versioni richieste di Git, tar, Python, make e gcc*" nel Manuale di Riferimento per i dettagli sul download o la creazione di un archivio di tali strumenti.

### *buildtools-extended*

Un set di binari *buildtools* esteso con strumenti di sviluppo aggiuntivi, come una versione necessaria del compilatore GCC per eseguire il sistema di build di OpenEmbedded.

Consultare il paragrafo "*Versioni richieste di Git, tar, Python, make e gcc*" nel Manuale di Riferimento per i dettagli sul download o la creazione di un archivio di tali strumenti.

### *buildtools-make*

Una variante di *buildtools*, che fornisce solo la versione necessaria di *make* per eseguire il sistema di build di OpenEmbedded.

### *Built-in Fragment*

Un built-in fragment [frammento nativo] è un tipo specifico di *Configuration Fragment* che influenza il valore di una singola variabile a livello globale. I *Built-in Fragments* non richiedono un file di configurazione separato, ma, come un normale *Configuration Fragment*, possono essere abilitati o disabilitati tramite l'utilità da riga di comando *bitbake-config-build*.

Quando viene dichiarato, un "built-in fragment" segue la seguente convenzione di nomenclatura:

```
<fragment>:<variable name>
```

Dove:

- `<fragment>` è il nome del frammento integrato.
- `<variable name>` è il nome della variabile da modificare tramite questo frammento.

Per esempio:

```
machine:MACHINE
```

Questo codice configura il Built-in Fragment *machine* per modificare il valore della variabile *MACHINE*.

L'impostazione della variabile *MACHINE* tramite questo frammento deve seguire questa sintassi:

```
machine/qemux86-64
```

Questo imposta il valore di *MACHINE* a *qemux86-64*.

In *OpenEmbedded-Core (OE-Core)*, l'elenco dei *Built-in Fragments* disponibili può essere ottenuto dalla variabile *OE\_FRAGMENTS\_BUILTIN*.

Per maggiori dettagli sui frammenti, consultare:

- La sezione *Using Configuration Fragments* del Manuale di Riferimento di Yocto Project per un elenco dei frammenti supportati da *OpenEmbedded Build System* e una guida rapida su come gestire i frammenti.
- Consultare la sezione *Creating New Configuration Fragments In Your Build* del Manuale di Sviluppo dei Task di Yocto Project per i dettagli su come creare nuovi frammenti nella build.

### *Classi*

File che forniscono incapsulamento logico ed ereditarietà, in modo che i pattern di uso comune possano essere definiti una sola volta e poi facilmente utilizzati in più ricette. Per informazioni di riferimento sulle classi di Yocto Project, consultare il capitolo "*Classi*". I file delle classi terminano con l'estensione *.bbclass*.

### File di Configurazione

File che contengono definizioni globali di variabili, variabili definite dall'utente e informazioni sulla configurazione hardware. Questi file indicano al sistema di build di OpenEmbedded cosa compilare e cosa includere nell'immagine per supportare una particolare piattaforma.

Configuration files end with a `.conf` filename extension. There are multiple types of configuration files, such as:

- The `build/conf/local.conf` configuration file in the *Build Directory* contains user-defined variables that affect every build.
- The `meta-poky/conf/distro/poky.conf` configuration file defines Yocto "distro" configuration variables used only when building with this policy. See the *Creating Your Own Distribution* section of the Yocto Project Reference Manual for more information.
- Machine configuration files, which are located in *Layer BSP*, define variables for specific hardware and are only used when building for that target (e.g. the `machine/beaglebone.conf` configuration file defines variables for the Texas Instruments ARM Cortex-A8 development board).
- *Configuration Fragments* such as `core/yocto/sstate-mirror-cdn` define snippets of configuration that can be enabled from the command-line.

See also the *Struttura della Directory Sorgente* section of the Yocto Project Reference Manual for more example of configuration files.

### Configuration Fragment

Un *Configuration Fragment* (chiamato anche *Configuration Fragment Standard*) è un *configuration file* che contiene istruzioni di configurazione, come ad esempio le assegnazioni di variabili, che influenzano la build a livello globale quando il frammento è abilitato. Per default, i frammenti di configurazione si trovano nella directory `conf/fragments/` di un *Layer*.

#### Nota

Un'altra tipologia di frammento da non confondere con i *Configuration Fragment Standard* sono i *Built-in Fragment*, utilizzati per assegnare un singolo valore a una variabile a livello globale.

Un frammento di *configuration file* deve contenere un riepilogo `[summary]` (`BB_CONF_FRAGMENT_SUMMARY`) e una descrizione (`BB_CONF_FRAGMENT_DESCRIPTION`) che ne spieghino lo scopo.

In *OpenEmbedded-Core (OE-Core)*, la posizione dei frammenti e le variabili necessarie per ciascun frammento sono specificate nel file `bitbake.conf` grazie alla direttiva `addfragments` e alle variabili `OE_FRAGMENTS`, `OE_FRAGMENTS_METADATA_VARS` e `OE_FRAGMENTS_BUILTIN`.

I frammenti possono essere elencati, abilitati e disabilitati tramite l'utility da riga di comando `bitbake-config-build`.

Per maggiori dettagli sui frammenti, consultare:

- La sezione *Using Configuration Fragments* del Manuale di Riferimento di Yocto Project per un elenco dei frammenti supportati da *OpenEmbedded Build System* e una guida rapida su come gestire i frammenti.

- Consultare la sezione *Creating New Configuration Fragments In Your Build* del Manuale di Sviluppo dei Task di Yocto Project per i dettagli su come creare nuovi frammenti nella build.

### Container Layer

A flexible definition that typically refers to a single Git checkout which contains multiple (and typically related) sub-layers which can be included independently in your project's *build/conf/bblayers.conf* file.

In some cases, such as with OpenEmbedded's *meta-openembedded* layer, the top level *meta-openembedded/* directory is not itself an actual layer, so you would never explicitly include it in a *build/conf/bblayers.conf* file; rather, you would include any number of its layer subdirectories, such as *meta-oe*, *meta-python* and so on.

On the other hand, some container layers (such as *meta-security*) have a top-level directory that is itself an actual layer, as well as a variety of sub-layers, both of which could be included in your *build/conf/bblayers.conf* file.

In entrambi i casi, l'espressione "container layer" viene semplicemente utilizzata per descrivere una struttura di directory che contiene più layer OpenEmbedded validi.

### Cross-Development Toolchain

In generale, una toolchain di cross-sviluppo è una raccolta di strumenti e utilità di sviluppo software che vengono eseguiti su un'architettura e consentono di sviluppare software per un'architettura diversa, o di destinazione [target]. Queste toolchain contengono cross-compiler, linker e debugger specifici per l'architettura target.

Yocto Project supporta due diverse toolchain di cross-development:

- Una toolchain utilizzata esclusivamente da e all'interno di BitBake durante la creazione di un'immagine per un'architettura target.
- Una toolchain riallocabile utilizzata dagli sviluppatori al di fuori di BitBake durante lo sviluppo di applicazioni destinate a un dispositivo specifico.

La creazione di queste toolchain è semplice e automatizzata. Per informazioni sui concetti relativi alle toolchain applicati a Yocto Project, consultare la sezione "*Generazione di Toolchain di Cross-Sviluppo*" nel Manuale Introduttivo e Concetti di Yocto Project. Ulteriori informazioni sull'utilizzo della toolchain riallocabile sono disponibili nel manuale *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)*.

### Extensible Software Development Kit (eSDK)

Un SDK custom per gli sviluppatori di applicazioni. Questo eSDK consente agli sviluppatori di integrare le proprie librerie e modifiche di programmazione nell'immagine, rendendo il codice disponibile ad altri sviluppatori di applicazioni.

Per informazioni sull'eSDK, consultare il manuale *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)*.

### Immagine

Una immagine [image] è un artefatto del processo di build di BitBake, data una raccolta di ricette e Metadati correlati. Le immagini sono l'output binario che viene eseguito su hardware specifico o su QEMU e sono utilizzate per casi d'uso specifici. Per un elenco dei tipi di immagine supportati da Yocto Project, consultare il capitolo "*Immagini*".

## Initramfs

Un filesystem in RAM iniziale (*Initramfs*) è un archivio *cpio*, eventualmente compresso, che viene estratto dal kernel Linux nella RAM in un'istanza speciale di *tmpfs*, utilizzata come filesystem root iniziale.

Questa tecnica sostituisce il vecchio disco RAM di inizializzazione ("initrd"), che si avviava su un dispositivo a blocchi emulato nella RAM, ma risultava meno efficiente a causa dell'overhead dovuto al passaggio attraverso un filesystem e alla necessità di duplicare il contenuto dei file a cui si accede nella cache dei file nella RAM, come avviene per qualsiasi dispositivo a blocchi.

### Nota

Per quanto riguarda i bootloader, le immagini *Initramfs* e "initrd" vengono comunque copiate nella RAM nello stesso modo. Per questo motivo, la maggior parte dei bootloader si riferisce alle immagini *Initramfs* come "initrd" o "init RAM disk".

Questo tipo di meccanismo viene tipicamente utilizzato per due motivi:

- Per avviare lo stesso binario del kernel su più sistemi che richiedono "device driver" differenti. L'immagine *Initramfs* viene quindi personalizzata per ogni tipo di sistema, includendo i moduli del kernel specifici necessari per accedere al filesystem root finale. Questa tecnica è utilizzata in tutte le distribuzioni GNU/Linux per desktop e server.
- Per un avvio più rapido. Poiché il filesystem root viene estratto nella RAM, l'accesso alle prime applicazioni nello spazio utente è molto più veloce rispetto all'inizializzazione di un dispositivo a blocchi, all'accesso a più blocchi da esso e all'attraversamento di un filesystem con il suo overhead. Ad esempio, questo permette di visualizzare una schermata iniziale molto presto e di occuparsi successivamente del montaggio del filesystem root finale e del caricamento dei driver del kernel meno critici in termini di tempo.

Questo archivio *cpio* può essere caricato nella RAM dal bootloader oppure incluso nel binario del kernel.

Per informazioni sulla creazione e l'utilizzo di un *Initramfs*, consultare la sezione "*Building an Initial RAM Filesystem (Initramfs) Image*" nel Manuale di Sviluppo dei Task di Yocto Project.

## Layer

Una raccolta di ricette correlate. I layer consentono di consolidare i metadati correlati per personalizzare la build. I layer isolano inoltre le informazioni utilizzate durante la build per architetture multiple. I layer sono gerarchici nella loro capacità di sovrascrivere le specifiche precedenti. È possibile includere un numero qualsiasi di layer disponibili da Yocto Project e personalizzare la build aggiungendo i layer desiderati. È possibile cercare nel "Layer Index" i layer utilizzati all'interno di Yocto Project.

Per informazioni introduttive sui layer, consultare la sezione "*Il Modello a Layer di Yocto Project*" nel Manuale Introduttivo e Concetti di Yocto Project. Per informazioni più dettagliate sui layer, consultare la sezione "*Comprendere e Creare i Layer*" nel Manuale di Sviluppo dei Task di Yocto Project. Per una discussione specifica sui layer BSP, consultare la sezione "*Layer BSP*" nella Guida degli Sviluppatori di Board Support Packages (BSP) di Yocto Project.

## LTS

Questo termine ("Long Term Support") significa "Supporto a lungo termine" e, nel contesto di Yocto Project,

corrisponde a versioni stabili selezionate per le quali vengono forniti aggiornamenti di bug e sicurezza per almeno quattro anni. Per maggiori dettagli, consultare la sezione *Versioni con Supporto a Lungo Termine*.

### Metadata

Un elemento chiave di Yocto Project sono i metadati utilizzati per costruire una distribuzione Linux, contenuti nei file che l'*OpenEmbedded Build System* analizza durante la creazione di un'immagine. In generale, i Metadati includono ricette, file di configurazione e altre informazioni relative alle istruzioni di compilazione [build], nonché i dati utilizzati per controllare cosa viene compilato e gli effetti della compilazione. I Metadati includono anche comandi e dati che indicano le versioni del software utilizzate, la loro provenienza e le modifiche o aggiunte al software stesso (patch o file ausiliari) utilizzate per correggere bug o personalizzare il software per un utilizzo specifico. OpenEmbedded-Core è un importante insieme di metadati validati.

Nel contesto del kernel ("kernel Metadata"), il termine si riferisce ai frammenti di configurazione del kernel e alle funzionalità contenute nel repository Git [yocto-kernel-cache](#).

### Mixin

Un layer *Mixin* è un layer che può essere creato dalla community per aggiungere una funzionalità specifica o supportare una nuova versione di un pacchetto per una release *LTS*. Per maggiori dettagli, consultare la sezione *Versioni con Supporto a Lungo Termine*.

### OpenEmbedded Build System

Il sistema di build utilizzato da Yocto Project, che impiega *Bitbake* come esecutore di task. Nella documentazione di Yocto Project, il sistema di build OpenEmbedded viene talvolta indicato semplicemente come "il sistema di build". Qualora vengano menzionati altri sistemi di build, come ad esempio un sistema di build host o target, la documentazione ne specifica chiaramente la differenza.

#### Nota

Per informazioni storiche su Poky, consultare il termine *Poky*.

### OpenEmbedded-Core (OE-Core)

OE-Core è un insieme di metadati composto da ricette, classi e file associati fondamentali, pensati per essere comuni a molti sistemi derivati da OpenEmbedded, incluso Yocto Project. OE-Core è un sottoinsieme curato di un repository originale sviluppato dalla comunità OpenEmbedded, ridotto a un insieme più piccolo e centrale di ricette continuamente validate. Il risultato è un insieme di ricette di base rigorosamente controllato e di qualità garantita.

È possibile consultare il codice sorgente di *OpenEmbedded-Core (OE-Core)* su [openembedded-core](#).

### Package

Nel contesto di Yocto Project, questo termine [pacchetto] si riferisce all'output impacchettato di una ricetta prodotto da BitBake (ovvero una "baked recipe"). Un pacchetto [package] è generalmente costituito dai binari compilati prodotti dai sorgenti di una ricetta. Si "cucina" (ndt: bake=cucinare ovvero compilare) qualcosa eseguendola tramite BitBake [ndt:CucinaBit].

È importante notare che il termine "pacchetto" [package] può, in generale, avere significati più sfumati. Ad esempio, i pacchetti a cui si fa riferimento nella sezione *"Pacchetti Richiesti per l'Host di Build"* sono binari compilati che, una volta installati, aggiungono funzionalità alla distribuzione Linux.

Un altro punto degno di nota è che storicamente, all'interno di Yocto Project, le ricette venivano chiamate pacchetti [package]; da qui l'esistenza di diverse variabili BitBake apparentemente denominate in modo errato (ad esempio, *PR*, *PV* e *PE*).

### Package Groups

Gruppi arbitrari di Ricette software. I "Package Group" [gruppi di pacchetti] vengono utilizzati per contenere ricette che, una volta compilate, solitamente svolgono una singola attività. Ad esempio, un gruppo di pacchetti potrebbe contenere le ricette per il software proprietario o a valore aggiunto di un'azienda. Oppure, il gruppo di pacchetti potrebbe contenere le ricette che abilitano la grafica. Un gruppo di pacchetti è essenzialmente un'altra ricetta. Poiché i file dei gruppi di pacchetti sono ricette, terminano con l'estensione `.bb`.

### Poky

Poky, che si pronuncia *Pochi*, è una distribuzione embedded di riferimento e una configurazione di test di riferimento. Poky offre quanto segue:

- Una distribuzione funzionale di base utilizzata per illustrare come personalizzare una distribuzione.
- Un mezzo per testare i componenti di Yocto Project (ovvero, Poky viene utilizzato per validare Yocto Project).

Poky non è una distribuzione a livello di prodotto. Piuttosto, è un buon punto di partenza per la personalizzazione.

#### Nota

Poky also used to be a repository containing the combination of *BitBake*, *OpenEmbedded-Core (OE-Core)*, the *meta-yocto* repository and the Yocto Project documentation -- which were combined with the *combo-layer* tool.

This repository is still hosted at <https://git.yoctoproject.org/poky> and is still updated for maintained releases that are older than Whinlatter (5.3). Newer releases now use `bitbake-setup` to clone and setup the initial *OpenEmbedded Build System* environment. For more information on how to use `bitbake-setup`, see the *Build Rapida di un'Immagine con lo Yocto Project* document. An alternative can be to setup the above repositories manually, by following the *Setting Up the Poky Reference Distro Manually* section of the Yocto Project Development Tasks Manual.

#### Nota

Poky è nato come un progetto open-source inizialmente sviluppato da OpenedHand. OpenedHand ha sviluppato Poky a partire dal sistema di build OpenEmbedded esistente per creare un sistema di build commercialmente supportato per Linux embedded. Dopo l'acquisizione di OpenedHand da parte di Intel Corporation, il progetto Poky è diventato la base per il sistema di build di Yocto Project.

### Ricetta

Un insieme di istruzioni per la creazione di pacchetti. Una ricetta [recipe] descrive da dove ottenere il codice sorgente, quali patch applicare, come configurare il codice sorgente, come compilarlo e così via. Le ricette descrivono anche le dipendenze per le librerie o per altre ricette. Le ricette rappresentano l'unità logica di esecuzione, ovvero il software da compilare e le immagini da creare, e utilizzano l'estensione di file `.bb`.



### Reference Kit

Un esempio funzionante di un sistema, che include un *BSP*, un *build host* e altri componenti, compatibile con hardware specifico.

### SBOM

Questo termine (*Software Bill of Materials*) indica la distinta base del software. Quando si distribuisce un software, la distinta base fornisce una descrizione di tutti i componenti utilizzati, le relative licenze, le dipendenze, le modifiche apportate e le vulnerabilità note corrette.

Questo documento può essere utilizzato dai destinatari del software per valutare la propria esposizione a problemi di conformità delle licenze e vulnerabilità di sicurezza.

Per maggiori dettagli, consultare l'articolo [Software Supply Chain](#) su Wikipedia.

Il sistema di build OpenEmbedded può generare tale documentazione per il progetto, in formato *SPDX*, basandosi su tutti i metadati utilizzati per creare le immagini software. Consultare la sezione "*Creating a Software Bill of Materials*" del Manuale di Sviluppo dei Task.

### Source Directory

Questo termine [Directory Sorgente] si riferisce alla struttura di directory creata a seguito della configurazione dell'ambiente per la creazione di immagini con Yocto Project, operazione che può essere eseguita in due modi:

- Utilizzando l'utilità da riga di comando `bitbake-setup` ([Setting Up The Environment With bitbake-setup](#)).
- Oppure configurando manualmente i *Layers* ([Setting Up the Poky Reference Distro Manually](#)).

In entrambi i casi, il risultato sarà un insieme di *Layers* e una *Build Directory*: questa è la directory sorgente per la build. La documentazione di solito indica questa directory con il nome "bitbake-builds".

Una struttura tipica per la *Source Directory* sarebbe:

```
bitbake-builds/
├── build/
└── layers/
```

Dove la directory `layers/` corrisponde alla directory contenente i *layer* del progetto, e la directory `build/` corrisponde alla *Build Directory*.

Presentiamo la struttura della *Source Directory* e i suoi componenti in dettaglio nella sezione *Struttura della Directory Sorgente* del Manuale di Riferimento di Yocto Project.

#### Nota

Il sistema di build OpenEmbedded non supporta nomi di file o directory contenenti spazi. Assicurarsi che la directory sorgente utilizzata non contenga questo tipo di nomi.

La directory *Source Directory* contiene *BitBake*, *OpenEmbedded-Core (OE-Core)* e altri file che supportano Yocto Project.

Di conseguenza, è necessario che la *Source Directory* sia presente sul sistema di sviluppo per poter sviluppare applicazioni con Yocto Project.



## SPDX

Questo termine sta per *Software Package Data Exchange* e viene utilizzato come standard aperto per fornire una *Software Bill of Materials (SBOM)* [distinta base software]. Questo standard è sviluppato nell'ambito del progetto [Linux Foundation](#) e viene utilizzato dal sistema di build OpenEmbedded per fornire una *SBOM* associata a ciascuna immagine software.

Per maggiori dettagli, consultare la pagina [SPDX page](#) di Wikipedia e la sezione "*Creating a Software Bill of Materials*" del Manuale di Sviluppo dei Task.

## SPDX License Expression

Uno standard definito da [SPDX](#) per esprimere come una o più licenze si applicano a un'opera.

La sintassi per un'espressione di licenza SPDX è definita nella [Specificazione SPDX](#).

## Sysroot

Durante la cross-compilazione, il file system target può avere una struttura e un contenuto diversi rispetto al sistema host. Il concetto di *sysroot* si riferisce a una directory che riproduce il file system target e può essere utilizzata per la cross-compilazione.

Nel contesto delle toolchain di cross-compilazione, una *sysroot* contiene tipicamente le librerie C e gli header del kernel, oltre ai binari compilati per la libreria C. Una *toolchain multilib* può contenere diverse varianti dei binari della libreria C, ciascuna compilata per un set di istruzioni target (come `armv5`, `armv7` e `armv8`), ed eventualmente ottimizzata per uno specifico core della CPU.

Nel contesto più specifico del sistema di build OpenEmbedded e di Yocto Project, ogni ricetta ha due *sysroot*:

- Un *sysroot target* contenente tutte le librerie e gli header **target** necessari per compilare la ricetta.
- Un *sysroot nativo* contenente tutti i file e gli eseguibili **host** necessari per compilare la ricetta.

Vedere le variabili `SYSROOT_*` che controllano la creazione e la memorizzazione dei *sysroot*.

## Task

Un'unità di esecuzione per ricetta per BitBake (ad esempio `do_compile`, `do_fetch`, `do_patch` e così via). Uno dei principali vantaggi del sistema di compilazione è che, poiché ogni ricetta in genere avvia l'esecuzione di numerosi task [attività], è del tutto possibile che molti task vengano eseguiti in parallelo, sia i task provenienti da ricette separate, quelli indipendenti all'interno della stessa ricetta, potenzialmente fino al livello di parallelismo del sistema di compilazione.

## Toaster

Un'interfaccia web per [OpenEmbedded Build System](#) di Yocto Project. L'interfaccia consente di configurare ed eseguire le build. Le informazioni relative alle build vengono raccolte e memorizzate in un database. Per informazioni su Toaster, consultare il [Manuale Utente di Toaster](#).

## Upstream

Riferimento al codice sorgente o ai repository che non si trovano localmente sul sistema di sviluppo, ma in un'area remota controllata dal manutentore del codice sorgente. Ad esempio, affinché uno sviluppatore possa lavorare su una specifica porzione di codice, deve prima ottenerne una copia da una sorgente "upstream".

## 6.4 Rilasci di Yocto Project e Iter dei Rilasci Stabili

Il processo di rilascio di Yocto Project è prevedibile e consiste in rilasci principali [major] e secondari [minor] (punto). Questo breve capitolo fornisce informazioni su come vengono denominati i rilasci, sul loro ciclo di vita e sulla loro stabilità.

### 6.4.1 Cadenza dei Rilasci Major e Minor

Yocto Project ha rilasci "major" (ad esempio la 6.1) con una cadenza di sei mesi, all'incirca ad aprile e ottobre di ogni anno. Ecco alcuni esempi di rilasci principali di YP con i relativi nomi in codice. Consultare la sezione "*Nomi in Codice delle Release Major*" per informazioni sui nomi in codice utilizzati per i rilasci principali [major].

- 4.1 ("Langdale")
- 4.0 ("Kirkstone")
- 3.4 ("Honister")

Sebbene la cadenza non sia mai perfetta, questa tempistica facilita rilasci regolari con cicli di QA rigorosi, senza sovraccaricare gli utenti con troppi nuovi rilasci. La cadenza di rilascio è prevedibile ed evita molte festività importanti in diverse aree geografiche.

Yocto project rilascia versioni minori (point) in modo non programmato, solitamente in seguito all'accumulo di un numero sufficiente di correzioni o miglioramenti significativi alla versione principale associata. Alcuni esempi di versioni minori precedenti sono:

- 4.1.3
- 4.0.8
- 3.4.4

Il punto della release indica un punto nel ramo della versione principale in cui un ciclo completo di controllo qualità e processo di rilascio convalida il contenuto del nuovo ramo [branch].

#### Nota

È importante notare che le patch possono essere integrate nei rami della versione stabile non appena disponibili.

### 6.4.2 Ciclo di Sviluppo

Come spiegato nella precedente sezione *Cadenza dei Rilasci Major e Minor*, una nuova release viene rilasciata ogni sei mesi.

Durante questo periodo di sei mesi, Yocto Project rilascia quattro release "Milestone" che rappresentano punti di riferimento distinti. Le release milestone vengono testate attraverso il processo *Test e Garanzia di Qualità*, che aiuta a individuare i problemi prima del rilascio effettivo.

L'intervallo di tempo tra le release milestone può variare, ma in genere sono distribuite uniformemente durante questo periodo di sei mesi.

Queste release milestone sono contrassegnate da una "M" maiuscola dopo il nome della release futura. Ad esempio, le release milestone "6.1M1", "6.1M2" e "6.1M3" vengono rilasciate prima della release "6.1" vera e propria.

**i Nota**

La quarta milestone (M4) non viene effettivamente rilasciata e annunciata, ma rappresenta un momento in cui il team di Controllo Qualità avvia il processo di *Test e Garanzia di Qualità* prima di etichettare e rilasciare la versione finale.

Dopo la terza release (M3), Yocto Project entra in **Feature Freeze**. Ciò significa che i manutentori di *OpenEmbedded-Core (OE-Core)*, *BitBake* e altri repository centrali smettono di accettare modifiche significative sul branch "master". Le modifiche che possono essere accettate sono piccoli aggiornamenti ai componenti principali e correzioni di bug/sicurezza.

Durante il periodo di Feature Freeze, viene creato e gestito separatamente un nuovo branch [ramo] per testare le nuove funzionalità e i miglioramenti ricevuti dai collaboratori, ma queste modifiche verranno integrate nel branch master solo dopo il rilascio della release.

### 6.4.3 Nomi in Codice delle Release Major

Ogni release major riceve un nome in codice che la identifica nei *I Repository del Codice Sorgente di Yocto Project*. L'idea è che i branch di *Metadata* con lo stesso nome in codice siano probabilmente compatibili e quindi funzionino insieme.

**i Nota**

I nomi in codice sono associati alle release principali perché un numero di release di Yocto Project (ad esempio 6.1) potrebbe entrare in conflitto con un determinato layer o schema di versioning aziendale. I nomi in codice sono univoci, interessanti e facilmente identificabili.

Anche alle release viene assegnata una versione nominale, ma il nome in codice viene utilizzato nei repository per questo scopo. Informazioni sulle release e sui nomi in codice di Yocto Project si trovano nella pagina [pagina dei rilasci](#).

La nostra [Informazioni sulla Release](#) descrive in dettaglio come migrare da una release di Yocto Project alla successiva.

### 6.4.4 Iter per il Rilascio Stabile

Una volta rilasciata, la release entra nel processo di rilascio stabile, momento in cui viene assegnata una persona come responsabile della manutenzione per quella release stabile. Questo responsabile monitora l'attività relativa alla release, esaminando e gestendo le patch proposte e le attività di backport. Solo le correzioni e i miglioramenti che sono stati prima applicati sul branch "master" (ovvero il ramo corrente in fase di sviluppo) vengono presi in considerazione per il backporting in una release stabile.

**i Nota**

L'attuale politica di Yocto Project in merito al backporting prevede di considerare solo le correzioni di bug e le patch di sicurezza. La politica stabilisce che le nuove funzionalità non vengono retroportate in una release stabile. Questa politica implica che gli aggiornamenti generici di versione delle ricette difficilmente verranno accettati.

per il backporting. L'eccezione a questa politica si verifica quando esiste una valida ragione, ad esempio quando la correzione è anche l'approccio preferito a monte [upstream].

### 6.4.5 Politiche di Accettazione delle Patch per le Release Stabili/LTS

Tutte le modifiche devono essere già state accettate nella release master corrente e in qualsiasi altra release ancora all'interno del suo periodo di supporto stabile.

#### Accettabile:

- Correzioni di sicurezza e CVE
- Correzioni di bug
- Aggiornamenti di versione che seguono una serie stabile o LTS upstream allineata alla release originale (in base alla compatibilità). Per maggiori dettagli, consultare [Aggiornamenti a Release Stabili](#).

#### Nota

Una volta che `UPSTREAM_STABLE_RELEASE_REGEX` è stato accettato per una ricetta, gli aggiornamenti di versione che corrispondono al modello accettato sono considerati accettabili per default (con la possibilità di rifiutarli se la versione upstream non segue le proprie linee guida per le versioni stabili).

#### Potenzialmente accettabili:

- Correzioni per rendere il codice sorgente compatibile con le distribuzioni appena rilasciate, ad esempio aggiornamenti del tarball *uninative* o correzioni di compilazione per una nuova versione di GCC sul *Build Host*.

#### Inaccettabile:

- Aggiornamenti di versione generali
- Nuove funzionalità
- Modifiche all'ABI/API
- Miglioramenti e refactoring dei metadati, a meno che non siano una dipendenza di una correzione necessaria

#### Nota

Eventuali eccezioni a queste regole devono essere approvate dal TSC.

### 6.4.6 Aggiornamenti a Release Stabili

Alcuni progetti upstream mantengono branch stabili che includono solo correzioni di bug e patch di sicurezza, in modo simile alla politica di rilascio stabile di Yocto Project. Per le ricette che seguono tali progetti upstream, è possibile eseguire *stable point release upgrades* [aggiornamenti a release stabili] (ad esempio, l'aggiornamento dalla versione 1.0.2 alla 1.0.3) anziché accettare solo patch retroportate. Questo è il meccanismo alla base della politica "accettabili: aggiornamenti di versione che seguono una serie stabile upstream" descritta sopra.

## Criteri per l'Approvazione degli Upstream

Impostando `UPSTREAM_STABLE_RELEASE_REGEX` per una ricetta, determinati aggiornamenti di versione possono essere considerati con sicurezza come aggiornamenti stabili secondo i criteri di OpenEmbedded. L'*Automated Upgrade Helper (AUH)* invierà automaticamente le patch per aggiornare le ricette con questa variabile impostata durante le release stabili.

### Nota

È comunque possibile inviare patch per aggiornare ricette senza questa variabile per i branch stabili, ma la soglia di accettazione è elevata. Il messaggio di commit deve giustificare che l'aggiornamento di versione segue la nostra politica per i branch stabili o che esiste un motivo eccezionale per effettuare l'aggiornamento.

Una ricetta può avere `UPSTREAM_STABLE_RELEASE_REGEX` impostato in base ai seguenti criteri:

1. **Esistono rami [branch] stabili upstream** --- il progetto upstream mantiene rami denominati con un componente di versione stabile, ed esiste la prova che questi rami raccolgono solo correzioni di bug e aggiornamenti di sicurezza (nessuna nuova funzionalità o modifica di ABI/API). Ad esempio, la versione 2.41.3 di util-linux ha tre parti nella sua versione e upstream ha rami come `stable/v2.41` con due parti. Ciò dimostra che gli incrementi nella terza parte (ad esempio da 2.41.3 a 2.41.4) sono release stabili. Allo stesso modo, systemd mantiene `stable/v259-stable`.

E almeno uno dei seguenti:

2. **Conferma del manutentore upstream** --- il manutentore del progetto upstream conferma esplicitamente che un incremento in una determinata parte della versione riguarda solo la correzione di bug.
3. **Prove storiche o di buon senso inequivocabili** --- la cronologia delle modifiche del progetto mostra chiaramente che una determinata classe di aggiornamenti di versione riguarda solo la correzione di bug, oppure è una convenzione ampiamente riconosciuta. Ad esempio, gli incrementi del suffisso `p` di openssh (da 10.2p1 a 10.2p2) e gli aggiornamenti di livello di patch di kmod sono storicamente rilasci che riguardano solo la correzione di bug.

### Nota

Le patch per impostare `UPSTREAM_STABLE_RELEASE_REGEX` vengono inviate prima al ramo master e seguono il normale processo di revisione. Una volta accettate su master, possono essere retroportate ai rami di rilascio stabili. Possono essere fatte delle eccezioni quando necessario, ad esempio impostando `UPSTREAM_STABLE_RELEASE_REGEX` su un ramo stabile per una ricetta che è stata successivamente rimossa su master.

## Come Funzionano le Espressioni Regolari per le Release Stabili

Il meccanismo di aggiornamento a punto stabile utilizza un *filter regex* [espressione regolare di filtro] per limitare il controllo della versione upstream, in modo che vengano considerate solo le versioni appartenenti alla stessa serie stabile. Quando una ricetta imposta `UPSTREAM_STABLE_RELEASE_REGEX`, l'infrastruttura di controllo della versione nei fetcher di BitBake (git, wget, crate) applica tale espressione regolare per filtrare le versioni upstream rilevate. Solo le versioni che corrispondono all'espressione regolare vengono considerate come potenziali aggiornamenti.

Ad esempio, se una ricetta è attualmente alla versione 1.4.2 e l'espressione regolare è `^1\.(4|5)\.(\d+)*$`, la versione 1.4.7 sarebbe una valida candidata all'aggiornamento, mentre la versione 1.5.0 non lo sarebbe.

Per le ricette la cui versione utilizza uno schema separato da punti, la classe `upstream-stable-release-point` può generare automaticamente questa espressione regolare. Per altri schemi di versioning, impostare `UPSTREAM_STABLE_RELEASE_REGEX` direttamente nella ricetta.

## 6.4.7 Versioni con Supporto a Lungo Termine

Mentre le versioni stabili sono supportate per una durata di sette mesi, alcune versioni specifiche sono ora supportate per un periodo più lungo da Yocto Project e sono chiamate versioni Long Term Support (*LTS*).

Quando vengono rilevati problemi significativi, le versioni *LTS* consentono di pubblicare correzioni non solo per la versione stabile corrente, ma anche per le versioni *LTS* ancora supportate. Le versioni stabili più vecchie che hanno raggiunto la fine del loro ciclo di vita [End of Life] (EOL) non riceveranno tali aggiornamenti.

Questo è iniziato con la versione 3.1 ("Dunfell"), rilasciata nell'aprile 2020, che il progetto inizialmente si era impegnato a supportare per due anni, ma questa durata è stata successivamente estesa a quattro anni.


Una nuova versione *LTS* viene rilasciata ogni due anni ed è supportata per quattro anni. Questo offre maggiore stabilità agli utenti del progetto e lascia più tempo per l'aggiornamento alla successiva versione *LTS*.

Le versioni *LTS* attualmente supportate sono:

- Versione 6.0 ("Wynose"), rilasciata a maggio 2026 e supportata fino ad aprile 2030.
- Versione 5.0 ("Scarthgap"), rilasciata ad aprile 2024 e supportata fino ad aprile 2028.

Consultare [https://wiki.yoctoproject.org/wiki/Stable\\_Release\\_and\\_LTS](https://wiki.yoctoproject.org/wiki/Stable_Release_and_LTS) per i dettagli sulla gestione delle versioni stabili e *LTS*.

Questa documentazione è stata creata per la versione Blacksail.



### **Nota**

In alcuni casi, la community può creare un layer per aggiungere una funzionalità specifica o supportare una nuova versione di un pacchetto per una versione *LTS*. Questo viene chiamato layer *Mixin*. Si tratta di layer sottili e specifici che possono essere sovrapposti a una release *LTS* per "integrare" una funzionalità specifica in quella build. Vengono creati in base alle necessità e gestiti da chi ne ha bisogno.

Le politiche di test di questi layer dipendono dalla loro diffusione e vengono determinate caso per caso. È possibile trovare alcuni layer *Mixin* nel repository *meta-lts-mixins*. Sebbene il Yocto Project fornisca l'hosting per questi repository, non si occupa del loro test. Altri layer *Mixin* potrebbero essere rilasciati altrove dalla community.

## 6.4.8 Test e Garanzia di Qualità

Parte del processo di sviluppo e rilascio di Yocto Project è la garanzia di qualità attraverso l'esecuzione di strategie di test. Le strategie di test forniscono al team di Yocto Project un modo per garantire che una release sia valida. Inoltre, poiché le strategie di test sono visibili agli sviluppatori, è possibile validare i propri progetti. Questa sezione fornisce una panoramica dell'infrastruttura di test disponibile utilizzata in Yocto Project. Per informazioni su come eseguire i test disponibili sui propri progetti, consultare la sezione "*Performing Automated Runtime Testing*" nel Manuale dell'Ambiente di Test di Yocto Project.

L'infrastruttura di QA/testing è talmente integrata nel progetto che gli sviluppatori principali la danno per scontata. L'infrastruttura è composta dai seguenti elementi:

- *bitbake-selftest*: Un comando standalone che esegue unit test su componenti chiave di BitBake e sui suoi fetcher.
- *sanity*: Questa classe, inclusa automaticamente, verifica la presenza di strumenti mancanti nell'ambiente di build (ad esempio *gcc*) o di errori di configurazione comuni, come ad esempio un parametro *MACHINE* impostato in modo errato.
- *insane*: Questa classe verifica la validità dell'output generato dalle build. Ad esempio, se la build è destinata a un target ARM, controlla se sono stati prodotti binari ARM. Se, ad esempio, la build produce binari PPC, allora c'è un problema.
- *testimage*: Questa classe esegue test a runtime sulle immagini dopo la loro creazione. I test vengono solitamente utilizzati con *QEMU* per avviare le immagini e verificare il risultato combinato dell'avvio e le relative funzionalità. Tuttavia, il test può anche utilizzare l'indirizzo IP di una macchina.
- *ptest*: Esegue test sui pacchetti prodotti durante la compilazione di un determinato software. Il test consente di eseguire i pacchetti all'interno di un'immagine target.
- *oe-selftest*: Testa combinazioni di invocazioni di BitBake. Questi test operano al di fuori del sistema di compilazione di OpenEmbedded. *oe-selftest* può eseguire tutti i test per default oppure test o suite di test selezionati.

In origine, gran parte di questi test veniva eseguita manualmente. Tuttavia, sono stati compiuti sforzi significativi per automatizzare i test in modo che più persone possano utilizzarli e il team di sviluppo di Yocto Project possa eseguirli più velocemente ed efficientemente.

Il principale strumento di compilazione automatica (*Autobuilder*) di Yocto Project testa pubblicamente il codice di ogni release di Yocto Project nei repository *openembedded-core*, *meta-yocto* e *bitbake*. I test vengono eseguiti sia per lo stato corrente del branch "master" sia per le patch inviate. I test per le patch inviate vengono solitamente eseguiti nel ramo "master-next" nei repository *openembedded-core*, *meta-yocto* e *bitbake*.

**i Nota**

È possibile trovare tutti questi rami in *I Repository del Codice Sorgente di Yocto Project*.

I test all'interno di questi rami pubblici garantiscono, in modo visibile a tutti, che tutte le principali architetture e ricette previste in OE-Core vengano compilate e funzionino correttamente.

Varie funzionalità, come `multilib`, le sottoarchitetture (ad esempio `x32`, `poky-tiny`, `musl`, `no-x11` e così via), `bitbake-selftest` e `oe-selftest`, vengono testate come parte del processo di controllo qualità di una release. Il test e la validazione completi di una release richiedono diverse ore ai worker di Autobuilder.

**i Nota**

I worker di Autobuilder non sono omogenei, il che significa che vengono eseguiti regolarmente test su una varietà di distribuzioni Linux. Autobuilder è limitato al test di configurazioni basate su QEMU e non di hardware reale.

Infine, oltre ai test di Autobuilder, il team di controllo qualità di Yocto Project esegue test anche su diverse piattaforme, incluso hardware reale, per garantire i risultati attesi.

## 6.5 Struttura della Directory Sorgente

La *Source Directory* [Directory Sorgente] è composta da numerosi file, directory e sottodirectory; comprenderne la posizione e il contenuto è fondamentale per utilizzare efficacemente il Yocto Project. Questo capitolo descrive la Source Directory e fornisce informazioni su file e directory.



**i Nota**

Il sistema di build OpenEmbedded non supporta nomi di file o directory contenenti spazi. Assicurarsi che la directory sorgente utilizzata non contenga questo tipo di nomi.

Nelle sezioni seguenti, si presume che i componenti principali della *Source Directory* siano organizzati come segue:

```

├─ build/
│   └─ ...
└─ layers/
    ├─ bitbake/
    ├─ meta-yocto/
    ├─ openembedded-core/
    └─ yocto-docs/

```

### 6.5.1 Componenti Principali di Primo Livello

Questa sezione descrive i componenti principali della *Source Directory*.

#### **bitbake/**

Questa directory include una copia di BitBake per facilità d'uso. La copia corrisponde solitamente alla versione stabile corrente di BitBake rilasciata dal progetto BitBake. BitBake, un interprete di *Metadata*, legge i Metadati di Yocto Project ed esegue i task [attività] definiti da tali dati. Gli errori sono generalmente causati da problemi nei Metadati e non da BitBake stesso.

Quando si esegue il comando `bitbake`, viene avviato l'eseguibile principale di BitBake (che si trova nella directory `bitbake/bin/`). L'esecuzione dello script di configurazione dell'ambiente (ad esempio, *oe-init-build-env*) aggiunge le directory `scripts/` e `bitbake/bin/` (in quest'ordine) alla variabile d'ambiente `PATH` della shell.

Per ulteriori informazioni su BitBake, consultare il [Manuale Utente di BitBake](#).

#### **build/**

Questa directory contiene i file di configurazione utente e l'output generato dal sistema di build OpenEmbedded nella sua configurazione standard, in cui l'albero dei sorgenti è combinato con l'output. La *Build Directory* viene creata inizialmente quando si esegue `source` lo script di configurazione dell'ambiente di build di OpenEmbedded (ovvero *oe-init-build-env*).

È anche possibile posizionare i file di output e di configurazione in una directory separata dalla *Source Directory*, specificando un nome di directory quando si esegue `source` lo script di configurazione. Per informazioni su come separare l'output dai file della Source Directory locale (comunemente descritta come una build "out of tree" [fuori albero]), consultare la sezione "*oe-init-build-env*".

Consultare la sezione "*The Build Directory --- build/*" per dettagli sul contenuto della *Build Directory*.

### `layers/yocto-docs/`

Il repository della documentazione di Yocto è ospitato in <https://git.yoctoproject.org/yocto-docs>.

Questa directory contiene il codice sorgente della documentazione di Yocto Project, nonché template e tool che consentono di generare versioni PDF e HTML dei manuali. Ogni manuale è contenuto in una propria sottocartella; ad esempio, i file per questo manuale di riferimento si trovano nella directory `ref-manual/`.

Questa directory non è obbligatoria per la compilazione con *BitBake*.

### `layers/openembedded-core/`

Il repository di *OpenEmbedded-Core (OE-Core)* è ospitato su <https://git.openembedded.org/openembedded-core>.

### `meta/`

Questa directory contiene i metadati minimi di base di *OpenEmbedded-Core (OE-Core)*. La directory contiene ricette, classi comuni e configurazione della macchina per target strettamente emulati (`qemux86`, `qemuarm`, e così via).

### `meta-selftest/`

Questa directory aggiunge ricette e file append aggiuntivi utilizzati dagli autotest di OpenEmbedded per verificare il comportamento del sistema di compilazione. Non è necessario aggiungere questo layer al file `build/conf/bblayers.conf` a meno che non si desideri eseguire gli autotest.

### `meta-skeleton/`

Questa directory contiene ricette template per lo sviluppo di BSP e kernel.

### `scripts/`

Questa directory contiene vari script di integrazione che implementano funzionalità aggiuntive nell'ambiente di Yocto Project (ad esempio, script QEMU). Lo script `oe-init-build-env` aggiunge questa directory all'inizio della variabile d'ambiente `PATH` della shell.

La directory `scripts` contiene script utili per contribuire a Yocto Project, come `create-pull-request` e `send-pull-request`.

### `oe-init-build-env`

Questo script configura l'ambiente di build di OpenEmbedded. Eseguendo questo script con il comando `source` nella shell, vengono apportate modifiche alla variabile `PATH` e vengono impostate altre variabili principali di BitBake in base alla directory di lavoro corrente. È necessario eseguire uno script di configurazione dell'ambiente prima di eseguire i comandi di BitBake. Lo script utilizza altri script presenti nella directory `scripts` per svolgere la maggior parte del lavoro.

Quando si esegue questo script, l'ambiente di Yocto Project viene configurato, viene creata una *Build Directory*, la directory di lavoro diventa la *Build Directory* e vengono presentati alcuni semplici suggerimenti su cosa fare successivamente, incluso un elenco di possibili target da compilare. Ecco un esempio:

```
$ source oe-init-build-env

### Shell environment set up for builds. ###

You can now run 'bitbake <target>'

Common targets are:
    core-image-minimal
    core-image-sato
    meta-toolchain
    meta-ide-support

You can also run generated QEMU images with a command like 'runqemu qemux86-64'
```

**i Nota**

Quando si utilizza [bitbake-setup](#), questo script viene eseguito indirettamente quando si esegue `init-build-env` che si trova nella directory di build di [Setup](#). Tuttavia, rispetto a `oe-init-build-env`, `init-build-env` di `bitbake-setup` non accetta argomenti, poiché si trova già in una *Build Directory*.

Per ulteriori informazioni, consultare la documentazione [Setting Up The Environment With bitbake-setup](#).

L'output di default dello script `oe-init-build-env` proviene dai file `conf-summary.txt` e `conf-notes.txt`, che si trovano nella directory `meta/conf/templates/default` di *OpenEmbedded-Core (OE-Core)*. Se si progetta una distribuzione personalizzata, è possibile includere versioni personalizzate di questi file di configurazione, in cui è possibile fornire un breve riepilogo e note dettagliate sull'utilizzo, come ad esempio un elenco dei target definiti dalla distribuzione. Per ulteriori informazioni, consultare la sezione "[Creating a Custom Template Configuration Directory](#)" del Manuale delle attività di sviluppo del progetto Yocto.

Per default, l'esecuzione di questo script senza l'argomento *Build Directory* crea la directory `build/` nella directory di lavoro corrente. Se si specifica l'argomento *Build Directory* quando si esegue lo script con `source`, si indica al sistema di build di OpenEmbedded di creare una *Build Directory* a propria scelta. Ad esempio, il seguente comando crea una *Build Directory* denominata `mybuilds/` al di fuori della *Source Directory*:

```
$ source oe-init-build-env ~/mybuilds
```

Il sistema di build OpenEmbedded utilizza i file di configurazione dei template, che si trovano per default nella directory `meta/conf/templates/default` in *OpenEmbedded-Core (OE-Core)*. Per ulteriori informazioni, consultare la sezione "[Creating a Custom Template Configuration Directory](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

**i Nota**

Il sistema di build OpenEmbedded non supporta nomi di file o directory contenenti spazi. Se si tenta di eseguire lo script `oe-init-build-env` da una *Source Directory* che contiene spazi nei nomi di file o directory, lo script

restituisce un errore indicando che il file o la directory non esiste. Assicurarsi di utilizzare una *Source Directory* priva di nomi contenenti spazi.

#### `layers/meta-yocto/`

Il repository `meta-yocto` è ospitato in <https://git.yoctoproject.org/meta-yocto>.

#### `meta-poky/`

A seconda dei metadati di *OpenEmbedded-Core (OE-Core)*, questa directory aggiunge i metadati necessari per definire la distribuzione di riferimento di Poky.

Nello specifico, contiene il *configuration file* della distribuzione per Poky: `conf/distro/poky.conf`.

#### `meta-yocto-bsp/`

Questa directory contiene i Board Support Package (BSP) di riferimento per l'hardware di Yocto Project. Per ulteriori informazioni sui BSP, consultare il manuale *Manuale del Board Support Package (BSP) di Yocto Project*.

## 6.5.2 La Directory di Build --- `build/`

Il sistema di build OpenEmbedded crea la *Build Directory* quando si esegue lo script di configurazione dell'ambiente di build `oe-init-build-env`. Se non si specifica un nome per la *Build Directory* durante l'esecuzione dello script di configurazione, il nome predefinito è `build/`.

Per le successive analisi ed elaborazioni, il nome della directory di Build è disponibile tramite la variabile `TOPDIR`.

#### `build/buildhistory/`

Il sistema di build OpenEmbedded crea questa directory quando si abilita la cronologia delle compilazioni tramite il file di classe `buildhistory`. La directory organizza le informazioni di compilazione in sottodirectory per immagini, pacchetti e SDK. Per informazioni sulla funzionalità di cronologia delle build, consultare la sezione "*Maintaining Build Output Quality with buildhistory*" nel Manuale di Sviluppo dei Task di Yocto Project.

#### `build/cache/`

Questa directory contiene diversi file interni utilizzati dal sistema di build OpenEmbedded. Il path di questa directory è definito dalla variabile `PERSISTENT_DIR`.

Contiene anche `sanity_info`, un file di testo che tiene traccia di importanti informazioni di compilazione, come i valori di `TMPDIR`, `SSTATE_DIR`, nonché il nome e la versione della distribuzione host.

Questa directory non deve essere condivisa tra diverse compilazioni. [build].

### Nota

La posizione di default del database *Equivalenza degli Hash* è questa directory (quando `BB_HASHSERVE` è impostato su `auto`). Se si deve condividere il database *Equivalenza degli Hash*, non condividere questo file e fare

invece riferimento al documento *Setting up a Hash Equivalence Server* del Manuale di Sviluppo dei Task di Yocto Project per configurare un server Hash Equivalence.

#### **build/conf/local.conf**

Questo file contiene le configurazioni utente locali per l'ambiente di build.

Ad esempio, è possibile sperimentare impostando (o aggiungendo) le variabili *DISTRO\_FEATURES* o *IMAGE\_FEATURES*, oppure adattare le configurazioni di compilazione per ricette specifiche impostando le variabili *PACKAGECONFIG* corrispondenti. Per pubblicare e condividere le modifiche apportate a questo file, si consiglia di inserirle in un *configuration file* della distribuzione oppure di creare *frammenti di configurazione* a partire dalle modifiche apportate qui.

Il *OpenEmbedded Build System* può creare il file *build/conf/local.conf* da un file *local.conf.sample* quando si esegue il comando `source` dello script di configurazione dell'ambiente di compilazione di livello superiore *oe-init-build-env*.

Il file sorgente *local.conf.sample* utilizzato dipende dalla variabile di script *TEMPLATECONF*, che per default è *meta/conf/templates/default* in *OpenEmbedded-Core (OE-Core)*. Poiché la variabile di script punta al file sorgente *local.conf.sample*, ciò implica che è possibile configurare l'ambiente di compilazione da qualsiasi layer impostando la variabile nello script di configurazione dell'ambiente di compilazione di livello superiore in questo modo:

```
TEMPLATECONF=your_layer/conf/templates/your_template_name
```

Una volta che il processo di compilazione riceve il file di esempio, utilizza `sed` per sostituire i valori finali `${OEROOT}` a tutti i valori `##OEROOT##`.

#### **Nota**

È possibile vedere come viene utilizzata la variabile *TEMPLATECONF* esaminando lo script *layers/openembedded-core/scripts/oe-setup-builddir* in *OpenEmbedded-Core (OE-Core)*.

#### **build/conf/bblayers.conf**

Questo file di configurazione definisce i *layer*, ovvero le strutture ad albero delle directory attraversate (o percorse) da BitBake. Il file *build/conf/bblayers.conf* utilizza la variabile *BBLAYERS* per elencare i layer che BitBake cerca.

Il sistema di build OpenEmbedded può crearlo a partire da un file *bblayers.conf.sample* quando si esegue il comando `source` sullo script di configurazione dell'ambiente di compilazione di livello superiore (ovvero *oe-init-build-env*).

Come per il file *build/conf/local.conf*, il file sorgente *bblayers.conf.sample* utilizzato dipende dalla variabile di script *TEMPLATECONF*, il cui valore predefinito è *meta/conf/templates/default*. Poiché la variabile di script punta al file sorgente *bblayers.conf.sample*, ciò implica che è possibile basare la build su qualsiasi layer impostando la variabile nello script di configurazione dell'ambiente di build di livello superiore come segue:

```
TEMPLATECONF=your_layer/conf/templates/your_template_name
```

Una volta che il processo di build ottiene il file di esempio, utilizza `sed` per sostituire i valori finali di `${OEROOT}` per tutte le occorrenze di `##OEROOT##`.

#### **i** Nota

È possibile visualizzare come la variabile `TEMPLATECONF` viene definita dallo script `scripts/oe-setup-builddir` in *OpenEmbedded-Core (OE-Core)*.

#### **build/conf/site.conf**

Questo file contiene le configurazioni specifiche del sito per l'ambiente di build [compilazione].

Ad esempio, si può modificare questo file per limitare il numero di thread utilizzati da *BitBake* (`BB_NUMBER_THREADS`) o impostare la posizione da cui desideri accedere ai file scaricati (`DL_DIR`).

Questo file può essere condiviso per più directory di build. Ad esempio, `bitbake-setup` crea un link simbolico al file `build/conf/site.conf`, che punta a un file comune `build/conf/auto.conf`:

```
|─ poky-master-poky-distro_poky-machine_qemux86-64/
|   └─ build/
|       └─ conf/
|           └─ site.conf -> ../../../../site.conf
|─ poky-master-poky-with-sstate-distro_poky-machine_qemux86-64/
|   └─ build/
|       └─ conf/
|           └─ site.conf -> ../../../../site.conf
|─ site.conf
```

In questo modo, le impostazioni specifiche del sito possono essere condivise tra diverse configurazioni di build.

**i Nota**

Per ulteriori informazioni su come utilizzare `bitbake-setup`, consultare il documento *Build Rapida di un'Immagine con lo Yocto Project*.

**build/conf/bblock.conf**

Questo file di configurazione viene generato da `bblock` e contiene le firme bloccate da `bblock`. Per default, non esiste e verrà creato alla prima esecuzione di `bblock`.

**build/conf/toolcfg.conf**

Questo file contiene variabili di configurazione che vengono modificate automaticamente da strumenti come `bitbake-config-build`. Questo file non deve essere modificato manualmente.

**build/conf/auto.conf**

Questo file è destinato all'uso in ambienti di "continuous integration", come l'*Autobuilder* di Yocto Project. Non deve essere creato o modificato durante l'esecuzione di build locali.

**build/downloads/**

Questa directory contiene i tarball del codice sorgente scaricati dal progetto upstream. È possibile riutilizzare la directory per più build o spostarla in un'altra posizione. È possibile controllare la posizione di questa directory tramite la variabile `DL_DIR`.

**build/sstate-cache/**

Questa directory contiene la cache di shared state [stato condivisa]. È possibile riutilizzare la directory per più build o spostarla in un'altra posizione. È possibile controllare la posizione di questa directory tramite la variabile `SSTATE_DIR`.

**build/tmp/**

Il sistema di build OpenEmbedded crea e utilizza questa directory per tutti gli output del sistema di build. La variabile `TMPDIR` punta a questa directory.

BitBake crea questa directory se non esiste. Come ultima risorsa, per ripulire una build e riavviarla da zero (esclusi i download), è possibile rimuovere tutto il contenuto della directory `tmp` o eliminarla completamente. In tal caso, è necessario rimuovere completamente anche la directory `build/sstate-cache`.

**build/tmp/buildstats/**

Questa directory memorizza le statistiche di compilazione generate dalla classe `buildstats`.

### `build/tmp/cache/`

Quando BitBake analizza i metadati (ricette e file di configurazione), memorizza nella cache i risultati in `build/tmp/cache/` per velocizzare le compilazioni future. I risultati vengono memorizzati per ogni singola macchina.

Durante le compilazioni successive, BitBake controlla ogni ricetta (insieme, ad esempio, a tutti i file inclusi o aggiunti ad essa) per verificare se sono state modificate. Le modifiche possono essere rilevate, ad esempio, tramite le variazioni dell'ora di modifica (mtime) del file e l'hashing del contenuto del file. Se non vengono rilevate modifiche al file, il risultato dell'analisi memorizzato nella cache viene riutilizzato. Se il file è stato modificato, viene rianalizzato.

### `build/tmp/deploy/`

Questa directory contiene tutti gli "end result" [risultati finali] del processo di build di OpenEmbedded. La variabile `DEPLOY_DIR` punta a questa directory. Per maggiori dettagli sul contenuto della directory `deploy`, consultare le sezioni "*Immagini*" e "*SDK per lo Sviluppo di Applicazioni*" nel Manuale Introduttivo e Concetti di Yocto Project.

### `build/tmp/deploy/deb/`

Questa directory contiene tutti i pacchetti `.deb` prodotti dal processo di compilazione. I pacchetti sono suddivisi in feed per diversi tipi di architettura.

### `build/tmp/deploy/rpm/`

Questa directory contiene tutti i pacchetti `.rpm` prodotti dal processo di compilazione. I pacchetti sono suddivisi in feed per diversi tipi di architettura.

### `build/tmp/deploy/ipk/`

Questa directory contiene i pacchetti `.ipk` prodotti dal processo di compilazione.

### `build/tmp/deploy/licenses/`

Questa directory contiene le informazioni di licenza dei pacchetti. Ad esempio, la directory contiene sottocartelle per `bash`, `busybox` e `glibc` (tra gli altri) che a loro volta contengono i relativi file di licenza `COPYING` con altre informazioni di licenza. Per informazioni sulle licenze, consultare la sezione "*Maintaining Open Source License Compliance During Your Product's Lifecycle*" nel Manuale di Sviluppo dei Task di Yocto Project.

### `build/tmp/deploy/spdx/`

Questa directory contiene file JSON in formato `SPDX` utilizzati per creare una Software Bill of Materials (*SBOM*) [distinta base], come spiegato in dettaglio nella sezione "*Creating a Software Bill of Materials*" del Manuale di Sviluppo dei Task di Yocto Project.

### `build/tmp/deploy/images/`

Questa directory contiene gli oggetti di output di base della build (considerali come gli "artefatti generati" dal processo di build), tra cui l'immagine del boot loader, il kernel, il filesystem root e altro ancora. Per caricare l'immagine risultante da una build su un dispositivo, consultare questa directory per trovare i componenti necessari.



Fare attenzione quando si eliminano i file in questa directory. È possibile eliminare in sicurezza le vecchie immagini da questa directory (ad esempio, `core-image-*`). Tuttavia, il kernel (`*zImage*`, `*uImage*`, ecc.), il bootloader e altri file supplementari potrebbero essere distribuiti qui prima della creazione dell'immagine. Poiché questi file non vengono prodotti direttamente dall'immagine, se si eliminano non verranno ricreati automaticamente quando si creerà nuovamente l'immagine.

Se si eliminano accidentalmente dei file in questa directory, sarà necessario forzarne la ricreazione. Per farlo, è necessario conoscere il target che li ha generati. Ad esempio, questi comandi ricompilano e ricreano i file del kernel:

```
$ bitbake -c clean virtual/kernel
$ bitbake virtual/kernel
```

#### **build/tmp/deploy/sdk/**

Il sistema di build OpenEmbedded crea questa directory per contenere gli script di installazione della toolchain che, una volta eseguiti, installano il sysroot corrispondente all'hardware target. Ulteriori informazioni su questi programmi di installazione sono disponibili nella sezione *"Building an SDK Installer"* del Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (eSDK).

#### **build/tmp/hosttools/**

Il sistema di build OpenEmbedded utilizza questa directory per creare link simbolici ad alcuni componenti host che possono essere richiamati all'interno dei task. Questi sono i componenti di base elencati nella sezione *Pacchetti Richiesti per l'Host di Build*. Questi componenti sono elencati anche nella variabile `HOSTTOOLS` e sono limitati a questo elenco per evitare la contaminazione dell'host.

#### **build/tmp/pkgdata/**

Il sistema di build OpenEmbedded utilizza questa directory per memorizzare i metadati dei pacchetti generati durante il task `do_packagedata`. I file memorizzati in questa directory contengono informazioni su ciascun pacchetto di output prodotto dal sistema di build OpenEmbedded e vengono utilizzati in diversi modi dal sistema di build, ad esempio per *"Viewing Package Information with oe-pkgdata-util"*.

#### **build/tmp/sstate-control/**

Il sistema di build OpenEmbedded utilizza questa directory per i file manifest dello "shared state" [stato condiviso]. Il codice di "shared state" utilizza questi file per registrare i file installati da ciascuna attività di stato condiviso, in modo che possano essere rimossi durante la pulizia della ricetta o quando sta per essere installata una versione più recente. Il sistema di build utilizza inoltre i manifest per rilevare e generare un warning quando i file di un task sovrascrivono quelli di un'altro.

#### **build/tmp/sysroots-components/**

Questa directory contiene il contenuto del sysroot che il task `do_prepare_recipe_sysroot` collega o copia nel sysroot specifico della ricetta per ciascuna ricetta elencata in `DEPENDS`. Il popolamento di questa directory viene gestito tramite lo "shared state" [stato condiviso], mentre il path è specificato dalla variabile `COMPONENTS_DIR`. A parte alcune circostanze eccezionali, la gestione della directory `sysroots-components` dovrebbe essere automatica e le ricette non dovrebbero fare riferimento direttamente a `build/tmp/sysroots-components`.

**build/tmp/sysroots/**

Nelle versioni precedenti del sistema di build OpenEmbedded, veniva creata una directory sysroot globale condivisa per ogni macchina, insieme a una directory sysroot nativa. Dalla versione 2.3 di Yocto Project, le directory sysroot si trovano in directory *WORKDIR* specifiche per ogni ricetta. Pertanto, la directory `build/tmp/sysroots/` non viene più utilizzata.

**Nota**

È comunque possibile popolare la directory `build/tmp/sysroots/` utilizzando il comando `bitbake build-sysroots` e, in alcuni casi, può essere utilizzata per garantire la compatibilità. Tuttavia, in generale, non è consigliabile popolare questa directory. È preferibile utilizzare directory sysroot specifiche per ogni ricetta.

**build/tmp/stamps/**

Questa directory contiene informazioni che BitBake utilizza a fini contabili per tenere traccia dei task eseguiti e del momento in cui sono stati eseguiti. La directory è suddivisa per architettura, nome del pacchetto e versione. Ecco un esempio:

```
stamps/all-poky-linux/distcc-config/1.0-r0.do_build-2fdd...2do
```

Sebbene i file nella directory siano vuoti, BitBake utilizza i nomi dei file e i timestamp a scopo di tracciamento.

Per informazioni su come BitBake utilizza i file di timestamp per determinare se un task deve essere rieseguito, consultare la sezione *"File Stamp e Riesecuzione dei Task"* nel Manuale Introduttivo e Concetti di Yocto Project.

**build/tmp/log/**

Questa directory contiene i log generali che non vengono altrimenti inseriti utilizzando la directory *WORKDIR* del pacchetto. Esempi di log sono l'output dei task `do_check_pkg` o `do_distro_check`. L'esecuzione di una build non implica necessariamente la creazione di questa directory.

**build/tmp/work/**

Questa directory contiene sottodirectory di lavoro specifiche per l'architettura dei pacchetti compilati da BitBake. Tutte le operazioni vengono eseguite dalla directory di lavoro appropriata. Ad esempio, il codice sorgente di un determinato pacchetto viene decompresso, patchato, configurato e compilato all'interno della sua directory di lavoro. All'interno della directory di lavoro, l'organizzazione si basa sul gruppo di pacchetti e sulla versione per cui il codice sorgente viene compilato, come definito da *WORKDIR*.

Vale la pena considerare la struttura di una tipica directory di lavoro. Ad esempio, si consideri `linux-yocto-kernel-3.0` sulla macchina `qemux86` compilata nell'ambito di Yocto Project. Per questo pacchetto, viene creata una directory di lavoro `tmp/work/qemux86-poky-linux/linux-yocto/3.0+git1+<...>`, denominata *WORKDIR*. All'interno di questa directory, il codice sorgente viene estratto in `sources/linux-qemux86-standard-build` e quindi patchato da Quilt. (Per ulteriori informazioni, consultare la sezione *"Using Quilt in Your Workflow"* del Manuale di Sviluppo dei Task di Yocto Project). All'interno della directo-

ry `linux-qemux86-standard-build`, vengono create le directory standard di Quilt `linux-3.0/patches` e `linux-3.0/.pc`, e si possono utilizzare i comandi standard di Quilt.

Vengono generate altre directory all'interno di *WORKDIR*. La directory più importante è `WORKDIR/temp/`, che contiene i file di log per ogni attività (`log.do_*.pid`) e gli script che BitBake esegue per ogni task (`run.do_*.pid`). La directory `WORKDIR/image/` è quella in cui il comando "make install" inserisce il suo output, che viene poi suddiviso in sottocartelle all'interno di `WORKDIR/packages-split/`.

**`build/tmp/work/tunearch/recipeName/version/`**

La directory di lavoro della ricetta --- `${WORKDIR}`.

Come descritto in precedenza nella sezione "*build/tmp/sysroots/*", a partire dalla versione 2.3 di Yocto Project, il sistema di build OpenEmbedded compila ogni ricetta nella propria directory di lavoro (ovvero *WORKDIR*). Il path alla directory di lavoro viene costruito utilizzando l'architettura della build specificata (ad esempio, *TUNE\_PKGARCH*, *MACHINE\_ARCH* o "allarch"), il nome della ricetta e la versione della ricetta (ad esempio, *PE:PV-PR*).

Ecco le principali sottodirectory all'interno di ciascuna directory di lavoro della ricetta:

- `${WORKDIR}/temp`: Contiene i file di log di ogni task eseguito per questa ricetta, i file "run" per ogni task eseguito, che contengono il codice eseguito, e un file `log.task_order`, che elenca l'ordine in cui sono state eseguiti i task.
- `${WORKDIR}/image`: Contiene l'output dei task *do\_install*, che corrisponde alla variabile `${D}` in tale task.
- `${WORKDIR}/pseudo`: Contiene il database pseudo e il log per tutti i task eseguiti in ambiente pseudo per la ricetta.
- `${WORKDIR}/sysroot-destdir`: Contiene l'output del task *do\_populate\_sysroot*.
- `${WORKDIR}/package`: Contiene l'output del task *do\_package* prima che venga suddiviso in singoli pacchetti.
- `${WORKDIR}/packages-split`: Contiene l'output del task *do\_package* dopo che è stato suddiviso in singoli pacchetti. Esistono sottocartelle per ogni singolo pacchetto creato dalla ricetta.
- `${WORKDIR}/recipe-sysroot`: Una directory contenente le dipendenze dal target della ricetta. Questa directory ha la stessa struttura del filesystem target e contiene le librerie che la ricetta potrebbe dover linkare (ad esempio, la libreria C).
- `${WORKDIR}/recipe-sysroot-native`: Una directory contenente le dipendenze native della ricetta. Questa directory contiene i tool necessari alla ricetta per la compilazione (ad esempio, il compilatore, Autoconf, libtool e così via).
- `${WORKDIR}/build`: Questa sottocartella si applica solo alle ricette che supportano build in cui il codice sorgente è separato dagli artefatti di build. Il sistema di build OpenEmbedded utilizza questa directory come directory di build separata (ovvero `${B}`).

**`build/tmp/work-shared/`**

Per motivi di efficienza, il sistema di build OpenEmbedded crea e utilizza questa directory per contenere le ricette che condividono una directory di lavoro con altre ricette. Viene utilizzata, ad esempio, per `gcc` e le sue varianti (ad esempio `gcc-cross`, `libgcc`, `gcc-runtime` e così via), oppure dalla classe *kernel* per rendere il codice sorgente

del kernel e gli artefatti di compilazione del kernel disponibili ai moduli del kernel esterni all'albero o ad altre ricette dipendenti dal kernel.

In pratica, solo poche ricette utilizzano la directory `work-shared`. Questa directory è particolarmente utile per le ricette che richiederebbero molto spazio di archiviazione se fossero condivise con il meccanismo standard *Sysroot*.

### 6.5.3 Metadati di OpenEmbedded-Core (OE-Core) --- `meta/`

Come accennato in precedenza, i *metadata OpenEmbedded-Core (OE-Core)* sono il nucleo di Yocto Project. Questi metadati sono suddivisi in diverse sezioni importanti:

#### `meta/classes*/`

Queste directory contengono i file `*.bbclass`. I file di classe vengono utilizzati per astrarre il codice comune in modo che possa essere riutilizzato da più pacchetti. Ogni pacchetto eredita il file *base*. Esempi di altre classi importanti sono *autotools\**, che in teoria consente a qualsiasi pacchetto abilitato per Autotools di funzionare con Yocto Project con il minimo sforzo. Un altro esempio è *kernel*, che contiene codice e funzioni comuni per lavorare con il kernel Linux. Funzioni come la generazione di immagini o il packaging hanno anch'esse i propri file di classe specifici, come *image*, *rootfs\** e *package\*.bbclass*.

Per informazioni di riferimento sulle classi, consultare il capitolo "*Classi*".

#### `meta/conf/`

Questa directory contiene il set principale di file di configurazione che partono da `bitbake.conf` e da cui vengono inclusi tutti gli altri file di configurazione. Osservando le istruzioni di inclusione alla fine del file `bitbake.conf`, si noterà che anche *build/conf/local.conf* viene caricato da lì. Sebbene `bitbake.conf` imposti i valori di default, è spesso possibile sovrascriverli utilizzando il file (*build/conf/local.conf*), il file di configurazione della macchina o il file di configurazione della distribuzione.

#### `meta/conf/machine/`

Questa directory contiene tutti i file di configurazione della macchina. Se si imposta `MACHINE = "qemux86"`, il sistema di build OpenEmbedded cerca il file `qemux86.conf` in questa directory. La directory *include* contiene vari dati comuni a diverse macchine. Per aggiungere il supporto per una nuova macchina a Yocto Project, consultare questa directory.

#### `meta/conf/distro/`

Il contenuto di questa directory controlla le configurazioni specifiche della distribuzione. Per Yocto Project, il file principale è `defaultsetup.conf`. Questa directory include le versioni e le definizioni di *SRCDATE* per le applicazioni configurate qui. Un esempio di configurazione alternativa potrebbe essere `poky-bleeding.conf`, sebbene questo file erediti principalmente la sua configurazione da Poky.

**meta/conf/machine-sdk/**

Il sistema di build OpenEmbedded cerca in questa directory i file di configurazione corrispondenti al valore di *SDK-MACHINE*. Per default, Yocto Project include file x86 a 32 e 64 bit che supportano alcuni host SDK. Tuttavia, è possibile estendere tale supporto ad altri host SDK aggiungendo ulteriori file di configurazione in questa sottodirectory all'interno di un altro layer.

**meta/files/**

Questa directory contiene i file di licenza comuni e diversi file di testo utilizzati dal sistema di compilazione, nonché i file *Wic files* che definiscono il layout delle immagini prodotte dalla compilazione. I file di testo contengono informazioni minime sul dispositivo ed elenchi di file e directory con permessi noti.

**meta/lib/**

Questa directory contiene il codice della libreria Python di OpenEmbedded utilizzato durante il processo di build. È abilitato tramite la direttiva `addpylib` nel file `meta/conf/layer.conf`. Per ulteriori informazioni, consultare [Extending Python Library Code](#).

**meta/recipes-bsp/**

Questa directory contiene tutti i collegamenti a hardware specifici o informazioni di configurazione hardware, come "u-boot" e "grub".

**meta/recipes-connectivity/**

Questa directory contiene librerie e applicazioni relative alla comunicazione con altri dispositivi.

**meta/recipes-core/**

Questa directory contiene tutto il necessario per creare un'immagine Linux di base funzionante, incluse le dipendenze più comuni.

**meta/recipes-devtools/**

Questa directory contiene tool utilizzati principalmente dal sistema di build. Tuttavia, questi strumenti possono essere utilizzati anche sui dispositivi target.

**meta/recipes-extended/**

Questa directory contiene applicazioni non essenziali che aggiungono funzionalità rispetto alle alternative presenti nel core. Potrebbe essere necessaria per sfruttare appieno tutte le funzionalità dei tool.

**meta/recipes-gnome/**

Questa directory contiene tutto ciò che riguarda il framework applicativo GTK+.

#### `meta/recipes-graphics/`

Questa directory contiene X e altre librerie di sistema relative alla grafica.

#### `meta/recipes-kernel/`

Questa directory contiene il kernel e le applicazioni e librerie generiche che hanno forti dipendenze dal kernel.

#### `meta/recipes-multimedia/`

Questa directory contiene codec e utility di supporto per audio, immagini e video.

#### `meta/recipes-rt/`

Questa directory contiene le ricette di pacchetti e immagini per l'utilizzo e il test del kernel `PREEMPT_RT`.

#### `meta/recipes-sato/`

Questa directory contiene il demo/reference UI/UX di Sato e le relative applicazioni e dati di configurazione.

#### `meta/recipes-support/`

Questa directory contiene le ricette utilizzate da altre ricette, ma non incluse direttamente nelle immagini (ovvero, dipendenze di altre ricette).

#### `meta/site/`

Questa directory contiene un elenco di risultati memorizzati nella cache per diverse architetture. Poiché alcuni risultati dei test di "autoconf" non possono essere determinati durante la cross-compilazione, in quanto i test non sono eseguibili su un sistema live, le informazioni contenute in questa directory vengono passate ad "autoconf" per le diverse architetture.

#### `meta/recipes.txt`

Questo file descrive il contenuto di `recipes-*`.

## 6.6 Classi

I file di classe vengono utilizzati per astrarre funzionalità comuni e condividerle tra più file di ricetta (`.bb`). Per utilizzare un file di classe, è sufficiente assicurarsi che la ricetta erediti la classe. Nella maggior parte dei casi, quando una ricetta eredita una classe, è sufficiente per abilitarne le funzionalità. Tuttavia, in alcuni casi potrebbe essere necessario impostare delle variabili o sovrascrivere alcuni comportamenti predefiniti all'interno della ricetta. Una classe può anche essere ereditata globalmente (in ogni ricetta) tramite la variabile *INHERIT*.

Qualsiasi *Metadata* che si trova solitamente in una ricetta può essere inserito anche in un file di classe. I file di classe sono identificati dall'estensione `.bbclass` e si trovano solitamente in una delle seguenti sottocartelle di un *layer*:

- `classes-recipe/` - classi destinate a essere ereditate singolarmente dalle ricette
- `classes-global/` - classi destinate a essere ereditate globalmente
- `classes/` - classi il cui contesto di utilizzo non è chiaramente definito

I file di classe possono anche essere indicati tramite *BUILDDIR* (ad esempio `build/`) nello stesso modo dei file `build/`nella directory`conf`. I file di classe vengono cercati in *BBPATH* utilizzando lo stesso metodo impiegato per la ricerca dei file `.conf`.

Questo capitolo tratta solo le classi più utili e importanti. Esistono altre classi all'interno delle directory `meta/classes*` di *OpenEmbedded-Core (OE-Core)*. Per ulteriori informazioni, è possibile consultare direttamente i file `.bbclass`.

### 6.6.1 allarch

La classe *allarch* viene ereditata dalle ricette che non producono output specifici per un'architettura. Questa classe disabilita le funzionalità normalmente necessarie per le ricette che producono binari eseguibili (come la compilazione del cross-compilatore e di una libreria C come prerequisiti e la separazione dei simboli di debug durante la fase di packaging).

#### Nota

A differenza di alcune ricette di distribuzione (ad esempio Debian), le ricette di OpenEmbedded che producono pacchetti dipendenti da ottimizzazioni tramite l'uso delle variabili *RDEPENDS* e *TUNE\_PKGARCH* non devono mai essere configurate per tutte le architetture utilizzando *allarch*. Questo accade anche se le ricette non producono output specifici per un'architettura.

Configurare tali ricette per tutte le architetture fa sì che i task *do\_package\_write\_\** abbiano firme diverse per le macchine con configurazioni diverse. Inoltre, si verificano ricompilazioni non necessarie ogni volta che viene creata un'immagine per una *MACHINE* diversa, anche quando la ricetta non cambia mai.

Per default, tutte le ricette ereditano le classi *base* e *package*, che abilitano le funzionalità necessarie per le ricette che producono output eseguibile. Se la ricetta, ad esempio, produce solo pacchetti contenenti file di configurazione, file multimediali o script (ad esempio Python e Perl), allora dovrebbe ereditare la classe *allarch*.

### 6.6.2 archiver

La classe *archiver* supporta il rilascio del codice sorgente e di altri materiali insieme ai file binari.

Per maggiori dettagli sulla classe sorgente *archiver*, consultare la sezione "*Maintaining Open Source License Compliance During Your Product's Lifecycle*" nel Manuale di Sviluppo dei Task di Yocto Project. È inoltre possibile consultare la variabile *ARCHIVER\_MODE* per informazioni sui flag variabili (varflags) che consentono di controllare la creazione dell'archivio.

### 6.6.3 autotools\*

Le classi *autotools\** supportano i pacchetti creati con GNU Autotools.

I pacchetti *autoconf*, *automake* e *libtool* introducono la standardizzazione. Questa classe definisce un insieme di task (ad esempio *configure*, *compile* e così via) che funzionano per tutti i pacchetti creati con Autotools. Di solito è sufficiente definire alcune variabili standard e poi semplicemente ereditare *autotools*. Queste classi possono funzionare anche con software che emula Autotools. Per ulteriori informazioni, consultare la sezione "*Building an Autotooled Package*" nel Manuale di Sviluppo dei Task di Yocto Project.

Per default, le classi *autotools\** utilizzano build out-of-tree (ovvero, `autotools.bbclass` viene compilato con `B != S`).

Se il software compilato da una ricetta non supporta l'utilizzo di build out-of-tree, è necessario che la ricetta erediti la classe *autotools-brokensep*. La classe *autotools-brokensep* si comporta allo stesso modo della classe *autotools\**, ma compila con `B == S`. Questo metodo è utile quando il supporto per le build out-of-tree non è presente o è difettoso.

**i Nota**

Si raccomanda di correggere e utilizzare il supporto per le build out-of-tree, se possibile.

È utile avere un'idea di come funzionano i task definite dalle classi *autotools\** e cosa fanno dietro le quinte.

- *do\_configure* --- rigenera lo script di configurazione (utilizzando `autoreconf`) e lo avvia con un set standard di argomenti utilizzati durante la compilazione incrociata. È possibile passare parametri aggiuntivi a *configure* tramite le variabili *EXTRA\_OECONF* o *PACKAGECONFIG\_CONFARGS*.
- *do\_compile* --- esegue `make` con argomenti che specificano il compilatore e il linker. È possibile passare argomenti aggiuntivi tramite la variabile *EXTRA\_OEMAKE*.
- *do\_install* --- esegue `make install` e passa in `${D}` come `DESTDIR`.

## 6.6.4 barebox

La classe *barebox* gestisce la compilazione del bootloader barebox.

Se un file denominato `defconfig` è incluso in *SRC\_URI*, verrà copiato in `.config` nella directory di build e utilizzato come configurazione barebox. Invece di fornire un file `defconfig`, è possibile impostare *BAREBOX\_CONFIG* con un file `defconfig` fornito dall'albero dei sorgenti di barebox. Se non vengono specificati né `defconfig` né *BAREBOX\_CONFIG*, la classe genererà un errore.

La classe *barebox* supporta i frammenti di configurazione e include internamente la classe *cmll* per fornire il supporto a *Kconfig* per barebox, abilitando i task come *do\_menuconfig* e *do\_diffconfig*.

I binari barebox generati vengono distribuiti in *DEPLOY\_DIR\_IMAGE* e installati in *BAREBOX\_INSTALL\_PATH* (`/boot` per default), diventando così parte del pacchetto base della ricetta. Questa configurazione supporta sia l'utilizzo dei binari barebox come artefatti indipendenti, sia la loro installazione in un rootfs. *BAREBOX\_BINARY* può essere utilizzato per selezionare un binario distinto da distribuire e installare. Se *barebox* è impostato come *EFI\_PROVIDER*, la classe utilizzerà `conf/image-uefi.conf` per definire i percorsi di installazione predefiniti e le convenzioni di denominazione.

L'ambiente barebox compilato può essere esteso aggiungendo file di ambiente a *BAREBOX\_ENV\_DIR*. La variabile *BAREBOX\_FIRMWARE\_DIR* consente di specificare la directory di ricerca dei blob del firmware, abilitando il caricamento di firmware aggiuntivi come TF-A o OP-TEE.



### 6.6.5 base

The *base* class is special in that every `.bb` file implicitly inherits the class. This class contains definitions for standard basic tasks such as fetching, unpacking, configuring (empty by default), compiling (runs any `Makefile` present), installing (empty by default) and packaging (empty by default). These tasks are often overridden or extended by other classes such as the *autotools\** class or the *package* class.

The class also contains some commonly used functions such as `oe_runmake`, which runs `make` with the arguments specified in *EXTRA\_OEMAKE* variable as well as the arguments passed directly to `oe_runmake`.

### 6.6.6 bash-completion

Sets up packaging and dependencies appropriate for recipes that build software that includes bash-completion data.

### 6.6.7 bin\_package

The *bin\_package* class is a helper class for recipes, that disables the *do\_configure* and *do\_compile* tasks and copies the content of the *S* directory into the *D* directory. This is useful for installing binary packages (e.g. RPM packages) by passing the package in the *SRC\_URI* variable and inheriting this class.

For RPMs and other packages that do not contain a subdirectory, you should set the *SRC\_URI* option `subdir` to *BP* so that the contents are extracted to the directory expected by the default value of *S*. For example:

```
SRC_URI = "https://example.com/downloads/somepackage.rpm;subdir=${BP}"
```

This class can also be used for tarballs. For example:

```
SRC_URI = "file://somepackage.tar.xz;subdir=${BP}"
```

The *bin\_package* class will copy the extracted content of the tarball from *S* to *D*.

This class assumes that the content of the package as installed in *S* mirrors the expected layout once installed on the target, which is generally the case for binary packages. For example, an RPM package for a library would usually contain the `usr/lib` directory, and should be extracted to `${S}/usr/lib/<library>.so.<version>` to be installed in *D* correctly.

#### Nota

The extraction of the package passed in *SRC\_URI* is not handled by the *bin\_package* class, but rather by the appropriate *fetcher* depending on the file extension.

### 6.6.8 binconfig

The *binconfig* class helps to correct paths in shell scripts.

Before `pkg-config` had become widespread, libraries shipped shell scripts to give information about the libraries and include paths needed to build software (usually named `LIBNAME-config`). This class assists any recipe using such scripts.

During staging, the OpenEmbedded build system installs such scripts into the `sysroots/` directory. Inheriting this class results in all paths in these scripts being changed to point into the `sysroots/` directory so that all builds that use the script use the correct directories for the cross compiling layout. See the `BINCONFIG_GLOB` variable for more information.

### 6.6.9 `binconfig-disabled`

An alternative version of the `binconfig` class, which disables binary configuration scripts by making them return an error in favor of using `pkg-config` to query the information. The scripts to be disabled should be specified using the `BINCONFIG` variable within the recipe inheriting the class.

### 6.6.10 `buildhistory`

The `buildhistory` class records a history of build output metadata, which can be used to detect possible regressions as well as used for analysis of the build output. For more information on using Build History, see the "[Maintaining Build Output Quality with buildhistory](#)" section in the Yocto Project Development Tasks Manual.

### 6.6.11 `buildstats`

The `buildstats` class records performance statistics about each task executed during the build (e.g. elapsed time, CPU usage, and I/O usage).

When you use this class, the output goes into the `BUILDSTATS_BASE` directory, which defaults to `${TMPDIR}/buildstats/`. You can analyze the elapsed time using `scripts/pybootchartgui/pybootchartgui.py`, which produces a cascading chart of the entire build process and can be useful for highlighting bottlenecks.

If you want to enable the class, you can add "`buildstats`" to the `USER_CLASSES` variable.

### 6.6.12 `buildstats-summary`

When inherited globally, prints statistics at the end of the build on sstate re-use. In order to function, this class requires the `buildstats` class be enabled.

### 6.6.13 `cargo`

The `cargo` class allows to compile Rust language programs using `Cargo`. Cargo is Rust's package manager, allowing to fetch package dependencies and build your program.

Using this class makes it very easy to build Rust programs. All you need is to use the `SRC_URI` variable to point to a source repository which can be built by Cargo, typically one that was created by the `cargo new` command, containing a `Cargo.toml` file, a `Cargo.lock` file and a `src` subdirectory.

If you want to build and package tests of the program, inherit the `ptest-cargo` class instead of `cargo`.

You will find an example (that show also how to handle possible git source dependencies) in the `zvariant_3.12.0.bb` recipe. Another example, with only crate dependencies, is the `utils-coreutils` recipe, which was generated by the `cargo-bitbake` tool.

This class inherits the `cargo_common` class.

### 6.6.14 `cargo_c`

The `cargo_c` class can be inherited by a recipe to generate a Rust library that can be called by C/C++ code. The recipe which inherits this class has to only replace `inherit cargo` by `inherit cargo_c`.

See the `rust-c-lib-example_git.bb` example recipe.

### 6.6.15 `cargo_common`

The `cargo_common` class is an internal class that is not intended to be used directly.

An exception is the "rust" recipe, to build the Rust compiler and runtime library, which is built by Cargo but cannot use the `cargo` class. This is why this class was introduced.

### 6.6.16 `cargo-update-recipe-crates`

The `cargo-update-recipe-crates` class allows recipe developers to update the list of Cargo crates in `SRC_URI` by reading the `Cargo.lock` file in the source tree.

To do so, create a recipe for your program, for example using `devtool`, make it inherit the `cargo` and `cargo-update-recipe-crates` and run:

```
bitbake -c update_crates recipe
```

This creates a `recipe-crates.inc` file that you can include in your recipe:

```
require ${BPN}-crates.inc
```

That's also something you can achieve by using the `cargo-bitbake` tool.

### 6.6.17 `ccache`

The `ccache` class enables the C/C++ Compiler Cache for the build. This class is used to give a minor performance boost during the build.

See <https://ccache.samba.org/> for information on the C/C++ Compiler Cache, and the `ccache.bbclass` file for details about how to enable this mechanism in your configuration file, how to disable it for specific recipes, and how to share `ccache` files between builds.

Recipes (including *native* ones) can make use of the host's `ccache` binary (via *HOSTTOOLS*) if the following configuration statements are provided in a *configuration file*:

```
ASSUME_PROVIDED += "ccache-native"
HOSTTOOLS += "ccache"
```

Recipes can also explicitly disable *Ccache* support even when the `ccache` class is enabled, by setting the `CCACHE_DISABLE` variable to "1".

Using the `ccache` class can lead to unexpected side-effects. Using this class is not recommended.

### 6.6.18 chrpath

The *chrpath* class is a wrapper around the "chrpath" utility, which is used during the build process for *nativesdk*, *cross*, and *cross-canadian* recipes to change RPATH records within binaries in order to make them relocatable.

### 6.6.19 cmake

The *cmake* class allows recipes to build software using the CMake build system. You can use the *EXTRA\_OECMAKE* variable to specify additional configuration options to pass to the *cmake* command line.

By default, the *cmake* class uses Ninja instead of GNU make for building, which offers better build performance. If a recipe is broken with Ninja, then the recipe can set the *OECMAKE\_GENERATOR* variable to `Unix Makefiles` to use GNU make instead.

If you need to install custom CMake toolchain files supplied by the application being built, you should install them (during *do\_install*) to the preferred CMake Module directory: `${D}${datadir}/cmake/modules/`.

### 6.6.20 cmake-qemu

The *cmake-qemu* class might be used instead of the *cmake* class. In addition to the features provided by the *cmake* class, the *cmake-qemu* class passes the `CMAKE_CROSSCOMPILING_EMULATOR` setting to *cmake*. This allows to use QEMU user-mode emulation for the execution of cross-compiled binaries on the host machine. For more information about `CMAKE_CROSSCOMPILING_EMULATOR` please refer to the [related section of the CMake documentation](#).

Not all platforms are supported by QEMU. This class only works for machines with `qemu-usermode` in the *Machine Features*. Using QEMU user-mode therefore involves a certain risk, which is also the reason why this feature is not part of the main *cmake* class by default.

One use case is the execution of cross-compiled unit tests with CTest on the build machine. If `CMAKE_CROSSCOMPILING_EMULATOR` is configured:

```
cmake --build --target test
```

works transparently with QEMU user-mode.

If the CMake project is developed with this use case in mind this works very nicely. This also applies to an IDE configured to use *cmake-native* for cross-compiling.

### 6.6.21 cml1

The *cml1* class provides basic support for the Linux kernel style build configuration system. "cml" stands for "Configuration Menu Language", which originates from the Linux kernel but is also used in other projects such as U-Boot and BusyBox. It could have been called "kconfig" too.

The CML configuration file location (`.config`) is by default expected to be in the build directory (*B*). This can be overridden with the *KCONFIG\_CONFIG\_ROOTDIR* variable.

### 6.6.22 `compress_doc`

Enables compression for manual and info pages. This class is intended to be inherited globally. The default compression mechanism is `gz` (gzip) but you can select an alternative mechanism by setting the `DOC_COMPRESS` variable.

### 6.6.23 `copyleft_compliance`

The `copyleft_compliance` class preserves source code for the purposes of license compliance. This class is an alternative to the `archiver` class and is still used by some users even though it has been deprecated in favor of the `archiver` class.

### 6.6.24 `copyleft_filter`

A class used by the `archiver` and `copyleft_compliance` classes for filtering licenses. The `copyleft_filter` class is an internal class and is not intended to be used directly.

### 6.6.25 `core-image`

The `core-image` class provides common definitions for the `core-image-*` image recipes, such as support for additional `IMAGE_FEATURES`.

### 6.6.26 `cpan*`

The `cpan*` classes support Perl modules.

Recipes for Perl modules are simple. These recipes usually only need to point to the source's archive and then inherit the proper class file. Building is split into two methods depending on which method the module authors used.

- Modules that use old `Makefile.PL`-based build system require `cpan.bbclass` in their recipes.
- Modules that use `Build.PL`-based build system require using `cpan_build.bbclass` in their recipes.

Both build methods inherit the `cpan-base` class for basic Perl support.

### 6.6.27 `create-spdx`

The `create-spdx` class provides support for automatically creating `SPDX SBOM` documents based upon image and SDK contents.

This class is meant to be inherited globally from a configuration file:

```
INHERIT += "create-spdx"
```

The toplevel `SPDX` output file is generated in JSON format as a `IMAGE-MACHINE.spdx.json` file in `tmp/ deploy/ images/ MACHINE/` inside the *Build Directory*. There are other related files in the same directory, as well as in `tmp/ deploy/ spdx`.

The exact behaviour of this class, and the amount of output can be controlled by the `SPDX_PRETTY`, `SPDX_INCLUDE_SOURCES` and other variables starting with `SPDX_`.

See the description of these variables and the "*Creating a Software Bill of Materials*" section in the Yocto Project Development Tasks Manual for more details.

### 6.6.28 `cross`

The `cross` class provides support for the recipes that build the cross-compilation tools.

### 6.6.29 `cross-canadian`

The `cross-canadian` class provides support for the recipes that build the Canadian Cross-compilation tools for SDKs. See the "*Generazione di Toolchain di Cross-Sviluppo*" section in the Yocto Project Overview and Concepts Manual for more discussion on these cross-compilation tools.

### 6.6.30 `crosssdk`

The `crosssdk` class provides support for the recipes that build the cross-compilation tools used for building SDKs. See the "*Generazione di Toolchain di Cross-Sviluppo*" section in the Yocto Project Overview and Concepts Manual for more discussion on these cross-compilation tools.

### 6.6.31 `cython`

The `cython` class can be used by Python recipes that require `Cython` as part of their build dependencies (`DEPENDS`).

### 6.6.32 `debian`

The `debian` class renames output packages so that they follow the Debian naming policy (i.e. `glibc` becomes `libc6` and `glibc-devel` becomes `libc6-dev`.) Renaming includes the library name and version as part of the package name.

If a recipe creates packages for multiple libraries (shared object files of `.so` type), use the `LEAD_SONAME` variable in the recipe to specify the library on which to apply the naming scheme.

### 6.6.33 `deploy`

The `deploy` class handles deploying files to the `DEPLOY_DIR_IMAGE` directory. The main function of this class is to allow the deploy step to be accelerated by shared state. Recipes that inherit this class should define their own `do_deploy` function to copy the files to be deployed to `DEPLOYDIR`, and use `addtask` to add the task at the appropriate place, which is usually after `do_compile` or `do_install`. The class then takes care of staging the files from `DEPLOYDIR` to `DEPLOY_DIR_IMAGE`.

### 6.6.34 `devicetree`

The `devicetree` class allows to build a recipe that compiles device tree source files that are not in the kernel tree.

The compilation of out-of-tree device tree sources is the same as the kernel in-tree device tree compilation process. This includes the ability to include sources from the kernel such as SoC `dtsti` files as well as C header files, such as `gpio.h`.

The `do_compile` task will compile two kinds of files:

- Regular device tree sources with a `.dts` extension.
- Device tree overlays, detected from the presence of the `/plugin/;` string in the file contents.

This class deploys the generated device tree binaries into `${DEPLOY_DIR_IMAGE}/devicetree/`. This is similar to what the *kernel-devicetree* class does, with the added `devicetree` subdirectory to avoid name clashes. Additionally, the device trees are populated into the `sysroot` for access via the `sysroot` from within other recipes.

By default, all device tree sources located in `DT_FILES_PATH` directory are compiled. To select only particular sources, set `DT_FILES` to a space-separated list of files (relative to `DT_FILES_PATH`). For convenience, both `.dts` and `.dtb` extensions can be used.

An extra padding is appended to non-overlay device trees binaries. This can typically be used as extra space for adding extra properties at boot time. The padding size can be modified by setting `DT_PADDING_SIZE` to the desired size, in bytes.

See *devicetree.bbclass* sources for further variables controlling this class.

Here is an excerpt of an example `recipes-kernel/linux/devicetree-acme.bb` recipe inheriting this class:

```
inherit devicetree
COMPATIBLE_MACHINE = "^mymachine$"
SRC_URI:mymachine = "file://mymachine.dts"
```

### 6.6.35 devshell

The *devshell* class adds the `do_devshell` task. Distribution policy dictates whether to include this class. See the "Using a Development Shell" section in the Yocto Project Development Tasks Manual for more information about using *devshell*.

### 6.6.36 devupstream

The *devupstream* class uses *BBCLASSEXTEND* to add a variant of the recipe that fetches from an alternative URI (e.g. Git) instead of a tarball. Here is an example:

```
BBCLASSEXTEND = "devupstream:target"
SRC_URI:class-devupstream = "git://git.example.com/example;branch=main"
SRCREV:class-devupstream = "abcd1234"
```

Adding the above statements to your recipe creates a variant that has *DEFAULT\_PREFERENCE* set to `-1`. Consequently, you need to select the variant of the recipe to use it. Any development-specific adjustments can be done by using the `class-devupstream` override. Here is an example:

```
DEPENDS:append:class-devupstream = " gperf-native"
do_configure:prepend:class-devupstream() {
    touch ${S}/README
}
```

The class currently only supports creating a development variant of the target recipe, not *native* or *nativesdk* variants.

The *BBCLASSEXTEND* syntax (i.e. `devupstream:target`) provides support for *native* and *nativesdk* variants. Consequently, this functionality can be added in a future release.

Support for other version control systems such as Subversion is limited due to BitBake's automatic fetch dependencies (e.g. `subversion-native`).

### 6.6.37 `externalsrc`

The `externalsrc` class supports building software from source code that is external to the OpenEmbedded build system. Building software from an external source tree means that the build system's normal fetch, unpack, and patch process is not used.

By default, the OpenEmbedded build system uses the `S` and `B` variables to locate unpacked recipe source code and to build it, respectively. When your recipe inherits the `externalsrc` class, you use the `EXTERNALSRC` and `EXTERNALSRC_BUILD` variables to ultimately define `S` and `B`.

By default, this class expects the source code to support recipe builds that use the `B` variable to point to the directory in which the OpenEmbedded build system places the generated objects built from the recipes. By default, the `B` directory is set to the following, which is separate from the source directory (`S`):

```
${WORKDIR}/${BPN}-${PV}/
```

See these variables for more information: `WORKDIR`, `BPN`, and `PV`,

For more information on the `externalsrc` class, see the comments in `meta/classes/externalsrc.bbclass` in *OpenEmbedded-Core (OE-Core)*. For information on how to use the `externalsrc` class, see the "*Building Software from an External Source*" section in the Yocto Project Development Tasks Manual.

### 6.6.38 `extrausers`

The `extrausers` class allows additional user and group configuration to be applied at the image level. Inheriting this class either globally or from an image recipe allows additional user and group operations to be performed using the `EXTRA_USERS_PARAMS` variable.

#### Nota

The user and group operations added using the `extrausers` class are not tied to a specific recipe outside of the recipe for the image. Thus, the operations can be performed across the image as a whole. Use the `useradd*` class to add user and group configuration to a specific recipe.

Here is an example that uses this class in an image recipe:

```
inherit extrausers
EXTRA_USERS_PARAMS = "\
    useradd -p '' tester; \
    groupadd developers; \
    userdel nobody; \
    groupdel -g video; \
    groupmod -g 1020 developers; \
    usermod -s /bin/sh tester; \
"
```



Here is an example that adds two users named "tester-jim" and "tester-sue" and assigns passwords. First on host, create the (escaped) password hash:

```
printf "%q" $(mkpasswd -m sha256crypt tester01)
```

The resulting hash is set to a variable and used in `useradd` command parameters:

```
inherit extrausers
PASSWD = "\$X\$ABC123\$A-Long-Hash"
EXTRA_USERS_PARAMS = "\
    useradd -p '${PASSWD}' tester-jim; \
    useradd -p '${PASSWD}' tester-sue; \
"
```

Finally, here is an example that sets the root password:

```
inherit extrausers
EXTRA_USERS_PARAMS = "\
    usermod -p '${PASSWD}' root; \
"
```

#### Nota

From a security perspective, hardcoding a default password is not generally a good idea or even legal in some jurisdictions. It is recommended that you do not do this if you are building a production image.

## 6.6.39 `features_check`

The *features\_check* class allows individual recipes to check for required and conflicting *DISTRO\_FEATURES*, *MACHINE\_FEATURES* or *COMBINED\_FEATURES*.

This class provides support for the following variables:

- *REQUIRED\_DISTRO\_FEATURES*
- *CONFLICT\_DISTRO\_FEATURES*
- *ANY\_OF\_DISTRO\_FEATURES*
- *REQUIRED\_MACHINE\_FEATURES*
- *CONFLICT\_MACHINE\_FEATURES*
- *ANY\_OF\_MACHINE\_FEATURES*
- *REQUIRED\_COMBINED\_FEATURES*
- *CONFLICT\_COMBINED\_FEATURES*
- *ANY\_OF\_COMBINED\_FEATURES*

If any conditions specified in the recipe using the above variables are not met, the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### 6.6.40 fontcache

The *fontcache* class generates the proper post-install and post-remove (postinst and postrm) scriptlets for font packages. These scriptlets call `fc-cache` (part of `Fontconfig`) to add the fonts to the font information cache. Since the cache files are architecture-specific, `fc-cache` runs using QEMU if the postinst scriptlets need to be run on the build host during image creation.

If the fonts being installed are in packages other than the main package, set *FONT\_PACKAGES* to specify the packages containing the fonts.

#### 6.6.41 fs-uuid

The *fs-uuid* class extracts UUID from `${ROOTFS}`, which must have been built by the time that this function gets called. The *fs-uuid* class only works on `ext` file systems and depends on `tune2fs`.

#### 6.6.42 gconf

The *gconf* class provides common functionality for recipes that need to install GConf schemas. The schemas will be put into a separate package (`${PN}-gconf`) that is created automatically when this class is inherited. This package uses the appropriate post-install and post-remove (postinst/postrm) scriptlets to register and unregister the schemas in the target image.

#### 6.6.43 gettext

The *gettext* class provides support for building software that uses the GNU *gettext* internationalization and localization system. All recipes building software that use *gettext* should inherit this class.

This class will configure recipes to build translations *unless*:

- the *USE\_NLS* variable is set to `no`, or
- the *INHIBIT\_DEFAULT\_DEPS* variable is set and the recipe inheriting the *gettext* class does not also inherit the *cross-canadian* class.

#### 6.6.44 github-releases

For recipes that fetch release tarballs from github, the *github-releases* class sets up a standard way for checking available upstream versions (to support `devtool upgrade` and the Automated Upgrade Helper (AUH)).

To use it, add "*github-releases*" to the inherit line in the recipe, and if the default value of *GITHUB\_BASE\_URI* is not suitable, then set your own value in the recipe. You should then use `${GITHUB_BASE_URI}` in the value you set for *SRC\_URI* within the recipe.

### 6.6.45 gnomebase

The *gnomebase* class is the base class for recipes that build software from the GNOME stack. This class sets *SRC\_URI* to download the source from the GNOME mirrors as well as extending *FILES* with the typical GNOME installation paths.

### 6.6.46 go

The *go* class supports building Go programs. The behavior of this class is controlled by the mandatory *GO\_IMPORT* variable, and by the optional *GO\_INSTALL* and *GO\_INSTALL\_FILTEROUT* ones.

To build a Go program with the Yocto Project, you can use the *go-helloworld\_0.1.bb* recipe as an example.

### 6.6.47 go-mod

The *go-mod* class allows to use Go modules, and inherits the *go* class.

See the associated *GO\_WORKDIR* variable.

### 6.6.48 go-mod-update-modules

The *go-mod-update-modules* class can be used in Go recipes and defines a *do\_update\_modules* task that can be run manually to update two files ("BPN" below corresponds to *BPN*):

- *BPN-go-mods.inc*: list of Go modules the recipe depends on.
- *BPN-licenses.inc*: list of licenses for each Go modules the recipe depends on.

These files can then updated automatically with the *do\_update\_modules* task.

### 6.6.49 go-vendor

The *go-vendor* class implements support for offline builds, also known as Go vendoring. In such a scenario, the module dependencies are downloaded during the *do\_fetch* task rather than when modules are imported, thus being coherent with Yocto's concept of fetching every source beforehand.

The dependencies are unpacked into the modules' *vendor* directory, where a manifest file is generated.

### 6.6.50 gobject-introspection

Provides support for recipes building software that supports GObject introspection. This functionality is only enabled if the "gobject-introspection-data" feature is in *DISTRO\_FEATURES* as well as "qemu-usermode" being in *MACHINE\_FEATURES*.

#### Nota

This functionality is *enabled* by default and, if not applicable, should be disabled through *DISTRO\_FEATURES\_OPTED\_OUT* or *MACHINE\_FEATURES\_OPTED\_OUT*, respectively.

### 6.6.51 grub-efi

The *grub-efi* class provides *grub-efi*-specific functions for building bootable images.

This class supports several variables:

- *INITRD*: Indicates list of filesystem images to concatenate and use as an initial RAM disk (initrd) (optional). Can be specified for each *LABEL*.
- *ROOTFS*: Indicates a filesystem image to include as the root filesystem (optional).
- *GRUB\_GFXSERIAL*: Set this to "1" to have graphics and serial in the boot menu.
- *LABELS*: A list of targets for the automatic configuration.
- *APPEND*: An override list of append strings for each *LABEL*.
- *GRUB\_TITLE*: A custom title for each *LABEL*. If a label does not have a custom title, the label is used as title for the GRUB menu entry.
- *GRUB\_OPTS*: Additional options to add to the configuration (optional). Options are delimited using semi-colon characters (;).
- *GRUB\_TIMEOUT*: Timeout before executing the default *LABEL* (optional).

Each *LABEL* defined in the *LABELS* variable creates a GRUB boot entry, and some variables can be defined individually per *LABEL*. The label specific override names are defined as *grub\_LABEL*.

For example, for a label *factory*, the override name would be *grub\_factory*. A custom GRUB menu entry titled "Factory Install" with the additional parameter *factory=yes* can be achieved as follows:

```
LABELS:append = " factory"
APPEND:grub_factory = "factory=yes"
GRUB_TITLE:grub_factory = "Factory Install"
```

### 6.6.52 gsettings

The *gsettings* class provides common functionality for recipes that need to install GSettings (glib) schemas. The schemas are assumed to be part of the main package. Appropriate post-install and post-remove (postinst/postrm) scriptlets are added to register and unregister the schemas in the target image.

### 6.6.53 gtk-doc

The *gtk-doc* class is a helper class to pull in the appropriate *gtk-doc* dependencies and disable *gtk-doc*.

### 6.6.54 gtk-icon-cache

The *gtk-icon-cache* class generates the proper post-install and post-remove (postinst/postrm) scriptlets for packages that use GTK+ and install icons. These scriptlets call *gtk-update-icon-cache* to add the fonts to GTK+'s icon cache. Since the cache files are architecture-specific, *gtk-update-icon-cache* is run using QEMU if the postinst scriptlets need to be run on the build host during image creation.

### 6.6.55 `gtk-immodules-cache`

The `gtk-immodules-cache` class generates the proper post-install and post-remove (postinst/postrm) scriptlets for packages that install GTK+ input method modules for virtual keyboards. These scriptlets call `gtk-update-icon-cache` to add the input method modules to the cache. Since the cache files are architecture-specific, `gtk-update-icon-cache` is run using QEMU if the postinst scriptlets need to be run on the build host during image creation.

If the input method modules being installed are in packages other than the main package, set `GTKIMMODULES_PACKAGES` to specify the packages containing the modules.

### 6.6.56 `gzipnative`

The `gzipnative` class enables the use of different native versions of `gzip` and `pigz` rather than the versions of these tools from the build host.

### 6.6.57 `image`

The `image` class helps support creating images in different formats. First, the root filesystem is created from packages using one of the `rootfs*.bbclass` files (depending on the package format used) and then one or more image files are created.

- The `IMAGE_FSTYPES` variable controls the types of images to generate.
- The `IMAGE_INSTALL` variable controls the list of packages to install into the image.

For information on customizing images, see the "*Customizing Images*" section in the Yocto Project Development Tasks Manual. For information on how images are created, see the "*Immagini*" section in the Yocto Project Overview and Concepts Manual.

### 6.6.58 `image-buildinfo`

The `image-buildinfo` class writes a plain text file containing build information to the target filesystem at `${sysconfdir}/buildinfo` by default (as specified by `IMAGE_BUILDINFO_FILE`). This can be useful for manually determining the origin of any given image. It writes out two sections:

1. *Build Configuration*: a list of variables and their values (specified by `IMAGE_BUILDINFO_VARS`, which defaults to `DISTRO` and `DISTRO_VERSION`)
2. *Layer Revisions*: the revisions of all of the layers used in the build.

Additionally, when building an SDK it will write the same contents to `/buildinfo` by default (as specified by `SDK_BUILDINFO_FILE`).

### 6.6.59 `image_types`

The `image_types` class defines all of the standard image output types that you can enable through the `IMAGE_FSTYPES` variable. You can use this class as a reference on how to add support for custom image output types.

By default, the `image` class automatically enables the `image_types` class. The `image` class uses the `IMGCLASSES` variable as follows:

```

IMGCLASSES = "rootfs_${IMAGE_PKGTYPE} image_types ${IMAGE_CLASSES}"
# Only Linux SDKs support populate_sdk_ext, fall back to populate_sdk_base
# in the non-Linux SDK_OS case, such as mingw32
inherit populate_sdk_base
IMGCLASSES += "${@(['', 'populate_sdk_ext'] ['linux' in d.getVar("SDK_OS")])}"
IMGCLASSES += "${@bb.utils.contains_any('IMAGE_FSTYPES', 'live iso hddimg', 'image-
↪live', '', d)}"
IMGCLASSES += "${@bb.utils.contains('IMAGE_FSTYPES', 'container', 'image-container
↪', '', d)}"
IMGCLASSES += "image_types_wic"
IMGCLASSES += "rootfs-postcommands"
IMGCLASSES += "image-postinst-intercepts"
IMGCLASSES += "overlayfs-etc"
inherit_defer ${IMGCLASSES}

```

The *image\_types* class also handles conversion and compression of images.

#### Nota

To build a VMware VMDK image, you need to add "wic.vmdk" to *IMAGE\_FSTYPES*. This would also be similar for Virtual Box Virtual Disk Image ("vdi") and QEMU Copy On Write Version 2 ("qcow2") images.

### 6.6.60 image-container

The *image-container* class is automatically inherited in *image* recipes that have the `container` image type in *IMAGE\_FSTYPES*. It provides relevant settings to generate an image ready for use with an OCI-compliant container management tool, such as *Podman* or *Docker*.

#### Nota

This class neither builds nor installs container management tools on the target. Those tools are available in the *meta-virtualization* layer.

You should set the *PREFERRED\_PROVIDER* for the Linux kernel to `linux-dummy` in a *configuration file*:

```
PREFERRED_PROVIDER_virtual/kernel = "linux-dummy"
```

Otherwise an error is triggered. If desired, the *IMAGE\_CONTAINER\_NO\_DUMMY* variable can be set to "1" to avoid triggering this error.

The `linux-dummy` recipe acts as a Linux kernel recipe but builds nothing. It is relevant to use as the preferred Linux kernel provider in this case as a container image does not need to include a Linux kernel. Selecting it as the preferred provider for the kernel will also decrease build time.

Using this class only deploys an additional `tar.bz2` archive to `DEPLOY_DIR_IMAGE`. This archive can be used in a container file (a file typically named `Dockerfile` or `Containerfile`). For example, to be used with [Podman](#) or [Docker](#), the container file could contain the following instructions:

```
FROM scratch
ADD ./image-container-qemux86-64.rootfs.tar.bz2 /
ENTRYPOINT /bin/sh
```

This is suitable to build a container using our generated root filesystem image.

### 6.6.61 `image-live`

This class controls building "live" (i.e. `HDDIMG` and `ISO`) images. Live images contain `syslinux` for legacy booting, as well as the bootloader specified by `EFI_PROVIDER` if `MACHINE_FEATURES` contains "efi".

Normally, you do not use this class directly. Instead, you add "live" to `IMAGE_FSTYPES`.

### 6.6.62 `insane`

The *insane* class adds a step to the package generation process so that output quality assurance checks are generated by the OpenEmbedded build system. A range of checks are performed that check the build's output for common problems that show up during runtime. Distribution policy usually dictates whether to include this class.

You can configure the sanity checks so that specific test failures either raise a warning or an error message. Typically, failures for new tests generate a warning. Subsequent failures for the same test would then generate an error message once the metadata is in a known and good condition. See the "[QA Error and Warning Messages](#)" Chapter for a list of all the warning and error messages you might encounter using a default configuration.

Use the `WARN_QA` and `ERROR_QA` variables to control the behavior of these checks at the global level (i.e. in your custom distro configuration). However, to skip one or more checks in recipes, you should use `INSANE_SKIP`. For example, to skip the check for symbolic link `.so` files in the main package of a recipe, add the following to the recipe. You need to realize that the package name override, in this example `${PN}`, must be used:

```
INSANE_SKIP:${PN} += "dev-so"
```

Please keep in mind that the QA checks are meant to detect real or potential problems in the packaged output. So exercise caution when disabling these checks.

The tests you can list with the `WARN_QA` and `ERROR_QA` variables are documented in the [QA Error and Warning Messages](#) document of the Yocto Project Reference Manual.

### 6.6.63 `kernel`

The *kernel* class handles building Linux kernels. The class contains code to build all kernel trees. All needed headers are staged into the `STAGING_KERNEL_DIR` directory to allow out-of-tree module builds using the *module* class.

If a file named `defconfig` is listed in `SRC_URI`, then by default *do\_configure* copies it as `.config` in the build directory, so it is automatically used as the kernel configuration for the build. This copy is not performed in case `.config` already exists there: this allows recipes to produce a configuration by other means in `do_configure:prepend`.

Each built kernel module is packaged separately and inter-module dependencies are created by parsing the `modinfo` output. If all modules are required, then installing the `kernel-modules` package installs all packages with modules and various other kernel packages such as `kernel-vmlinux`.

The *kernel* class contains logic that allows you to embed an initial RAM filesystem (*Initramfs*) image when you build the kernel image. For information on how to build an *Initramfs*, see the "*Building an Initial RAM Filesystem (Initramfs) Image*" section in the Yocto Project Development Tasks Manual.

Various other classes are used by the *kernel* and *module* classes internally including the *kernel-arch* and *module-base* classes.

### 6.6.64 kernel-arch

The *kernel-arch* class sets the `ARCH` environment variable for Linux kernel compilation (including modules).

### 6.6.65 kernel-devicetree

The *kernel-devicetree* class, which is inherited by the *kernel* class, supports device tree generation.

Its behavior is mainly controlled by the following variables:

- *KERNEL\_DEVICETREE\_BUNDLE*: whether to bundle the kernel and device tree
- *KERNEL\_DTBDEST*: directory where to install DTB files
- *KERNEL\_DTBVENDORED*: whether to keep vendor subdirectories
- *KERNEL\_DTC\_FLAGS*: flags for `dtc`, the Device Tree Compiler
- *KERNEL\_PACKAGE\_NAME*: base name of the kernel packages

### 6.6.66 kernel-fit-image

The *kernel-fit-image* class provides support to pack a kernel image, device trees, a U-boot script, an *Initramfs* and additional loadables into a single FIT image. In theory, a FIT image can support any number of kernels, U-boot scripts, *Initramfs*, and device trees. However, *kernel-fit-image* currently only supports limited usecases: just one kernel image, an optional U-boot script, an optional *Initramfs*, and any number of device trees and loadables.

The FIT image is created by a recipe which inherits the *kernel-fit-image* class. One such example is the `linux-yocto-fitimage` recipe which creates a FIT image for the Linux Yocto kernel. Additionally, it is required that *KERNEL\_CLASSES* is set to include *kernel-fit-extra-artifacts*. The *kernel-fit-extra-artifacts* class exposes the required kernel artifacts to the *DEPLOY\_DIR\_IMAGE* which are used by the *kernel-fit-image* class to create the FIT image.

The simplest example for building a FIT image is to add:

```
KERNEL_CLASSES += "kernel-fit-extra-artifacts"
```

to the machine *configuration file* and to execute:

```
bitbake linux-yocto-fitimage
```



This results in a `fitImage` file deployed to the `DEPLOY_DIR_IMAGE` directory and a `linux-yocto-fitimage` package which can be installed.

The same approach works for all variants of the `linux-yocto` kernel. For example, if the `linux-yocto-rt` kernel should be used, add the following lines to the machine configuration file:

```
KERNEL_CLASSES += "kernel-fit-extra-artifacts"
PREFERRED_PROVIDER_virtual/kernel = "linux-yocto-rt"
```

The FIT image, this time including the RT kernel, is built again by calling:

```
bitbake linux-yocto-fitimage
```

For other kernels provided by other layers, the same approach would work. However, it is usually more intuitive to add a custom FIT image recipe next to the custom kernel recipe. For example, if a layer provides a `linux-vanilla` recipe, a `linux-vanilla-fitimage` recipe may be added as well. The `linux-vanilla-fitimage` recipe can be created as a customized copy of the `linux-yocto-fitimage` recipe.

Usually the kernel is built as a dependency of an image. If the FIT image should be used as a replacement for the kernel image which is installed in the root filesystem, then the following variables can be set e.g. in the machine configuration file:

```
# Create and deploy the vmlinux artifact which gets included into the FIT image
KERNEL_CLASSES += "kernel-fit-extra-artifacts"

# Do not install the kernel image package
RRECOMMENDS:${KERNEL_PACKAGE_NAME}-base = ""

# Install the FIT image package
MACHINE_ESSENTIAL_EXTRA_RDEPENDS += "linux-yocto-fitimage"

# Configure the image.bbclass to depend on the FIT image instead of only
# the kernel to ensure the FIT image is built and deployed with the image
KERNEL_DEPLOY_DEPEND = "linux-yocto-fitimage:do_deploy"
```

The *kernel-fit-image* class processes several variables that allow configuration:

- The options for the device tree compiler passed to `mkimage -D` when creating the FIT image are specified using the `UBOOT_MKIMAGE_DTCOPTS` variable.
- Only a single kernel can be added to the FIT image created by *kernel-fit-image* and it is a mandatory component of the FIT image. The address where the kernel image is to be loaded by U-Boot is specified by `UBOOT_LOADADDRESS` and the entrypoint by `UBOOT_ENTRYPOINT`. Setting `FIT_ADDRESS_CELLS` to "2" is necessary if such addresses are 64 bit ones.
- Multiple device trees can be added to the FIT image created by *kernel-fit-image* and the device tree is optional. The address where the device tree is to be loaded by U-Boot is specified by `UBOOT_DTBO_LOADADDRESS` for device tree overlays and by `UBOOT_DTB_LOADADDRESS` for device tree binaries.
- Only a single *Initramfs* can be added to the FIT image created by *kernel-fit-image*. The *Initramfs* in FIT is optional. The address where the RAM disk image is to be loaded by U-Boot is specified by

`UBOOT_RD_LOADADDRESS` and the entrypoint by `UBOOT_RD_ENTRYPOINT`. The *Initramfs* is added to the FIT image when `INITRAMFS_IMAGE` is specified.

- It's recommended to add the *Initramfs* and the kernel image as independent image nodes to the FIT image. Bundling a RAM disk image with the kernel image and including the bundle (`INITRAMFS_IMAGE_BUNDLE` set to "1") in the FIT image is possible. However, this approach has the disadvantage that any change to the RAM disk image necessitates rebuilding the kernel image. This process requires the full kernel build directory, which is kind of incompatible with the `SSTATE_DIR` and, consequently, with SDKs.
- Only a single U-Boot boot script can be added to the FIT image created by *kernel-fit-image*. The boot script is optional. The boot script is specified in the ITS file as a text file containing U-Boot commands. When using a boot script the recipe which inherits the *kernel-fit-image* class should add the script to `SRC_URI` and set the `FIT_UBOOT_ENV` variable to the name of the file like the following:

```
FIT_UBOOT_ENV = "boot.txt"
SRC_URI += "file://${FIT_UBOOT_ENV}"
```

At run-time, U-boot's boot command can be configured to load the boot script from the FIT image and source it.

- Multiple additional loadables (e.g.: firmwares for auxiliary processors) can be added to the FIT image created by *kernel-fit-image*. The addition of loadables is optional. The loadables are specified using the `FIT_LOADABLES` variable; each of them can then be configured through flags on the following variables: `FIT_LOADABLE_ARCH`, `FIT_LOADABLE_COMPRESSION`, `FIT_LOADABLE_DESCRIPTION`, `FIT_LOADABLE_ENTRYPOINT`, `FIT_LOADABLE_FILENAME`, `FIT_LOADABLE_LOADADDRESS`, `FIT_LOADABLE_OS` and `FIT_LOADABLE_TYPE`. All loadables specified in this way will be added to all configurations present in the FIT image.
- The FIT image generated by the *kernel-fit-image* class is signed when the variables `UBOOT_SIGN_ENABLE`, `UBOOT_MKIMAGE_DTCOPTS`, `UBOOT_SIGN_KEYDIR` and `UBOOT_SIGN_KEYNAME` are set appropriately. The default values used for `FIT_HASH_ALG` and `FIT_SIGN_ALG` in *kernel-fit-image* are "sha256" and "rsa2048" respectively. The keys for signing the FIT image can be generated using the *kernel-fit-image* class when both `FIT_GENERATE_KEYS` and `UBOOT_SIGN_ENABLE` are set to "1".

## 6.6.67 kernel-fit-extra-artifacts

The *kernel-fit-extra-artifacts* class exposes the required kernel artifacts to the `DEPLOY_DIR_IMAGE` directory. These artifacts are used by the *kernel-fit-image* class to create a FIT image that can include the kernel, device trees, an optional U-Boot script, and an optional Initramfs.

This class is typically included by adding it to the `KERNEL_CLASSES` variable in your kernel recipe or machine configuration when building FIT images. It ensures that all necessary files are available for packaging into the FIT image, such as the kernel binary, device tree blobs (DTBs), and other related files.

For example, to enable this class, set:

```
KERNEL_CLASSES += "kernel-fit-extra-artifacts"
```

This is required when using the *kernel-fit-image* class to generate FIT images for your kernel.

### 6.6.68 `kernel-grub`

The *kernel-grub* class updates the boot area and the boot menu with the kernel as the priority boot mechanism while installing a RPM to update the kernel on a deployed target.

### 6.6.69 `kernel-module-split`

The *kernel-module-split* class provides common functionality for splitting Linux kernel modules into separate packages.

### 6.6.70 `kernel-uboot`

The *kernel-uboot* class provides support for building from vmlinux-style kernel sources.

### 6.6.71 `kernel-uimage`

The *kernel-uimage* class provides support to pack uImage.

### 6.6.72 `kernel-yocto`

The *kernel-yocto* class provides common functionality for building from linux-yocto style kernel source repositories.

### 6.6.73 `kernel-yocto-rust`

The *kernel-yocto-rust* class creates the necessary Rust Linux kernel dependencies and ensures that they are available by running `make rustavailable` from the Linux kernel source tree.

### 6.6.74 `kernelsrc`

The *kernelsrc* class sets the Linux kernel source and version.

### 6.6.75 `lib_package`

The *lib\_package* class supports recipes that build libraries and produce executable binaries, where those binaries should not be installed by default along with the library. Instead, the binaries are added to a separate `${PN}-bin` package to make their installation optional.

### 6.6.76 `libc*`

The *libc\** classes support recipes that build packages with `libc`:

- The *libc-common* class provides common support for building with `libc`.
- The *libc-package* class supports packaging up `glibc` and `eglibc`.

### 6.6.77 `license`

The *license* class provides license manifest creation and license exclusion. This class is enabled by default using the default value for the *INHERIT\_DISTRO* variable.

### 6.6.78 linuxloader

Provides the function `linuxloader()`, which gives the value of the dynamic loader/linker provided on the platform. This value is used by a number of other classes.

### 6.6.79 logging

The *logging* class provides the standard shell functions used to log messages for various BitBake severity levels (i.e. `bbplain`, `bbnote`, `bbwarn`, `bberror`, `bbfatal`, and `bbdebug`).

This class is enabled by default since it is inherited by the *base* class.

### 6.6.80 meson

The *meson* class allows to create recipes that build software using the *Meson* build system. You can use the *MESON\_BUILDTYPE*, *MESON\_TARGET* and *EXTRA\_OEMESON* variables to specify additional configuration options to be passed using the `meson` command line.

### 6.6.81 metadata\_scm

The *metadata\_scm* class provides functionality for querying the branch and revision of a Source Code Manager (SCM) repository.

The *base* class uses this class to print the revisions of each layer before starting every build. The *metadata\_scm* class is enabled by default because it is inherited by the *base* class.

### 6.6.82 mime

The *mime* class generates the proper post-install and post-remove (postinst/postrm) scriptlets for packages that install MIME type files. These scriptlets call `update-mime-database` to add the MIME types to the shared database.

### 6.6.83 mime-xdg

The *mime-xdg* class generates the proper post-install and post-remove (postinst/postrm) scriptlets for packages that install `.desktop` files containing `MimeType` entries. These scriptlets call `update-desktop-database` to add the MIME types to the database of MIME types handled by desktop files.

Thanks to this class, when users open a file through a file browser on recently created images, they don't have to choose the application to open the file from the pool of all known applications, even the ones that cannot open the selected file.

If you have recipes installing their `.desktop` files as absolute symbolic links, the detection of such files cannot be done by the current implementation of this class. In this case, you have to add the corresponding package names to the *MIME\_XDG\_PACKAGES* variable.

### 6.6.84 mirrors

The *mirrors* class sets up some standard *MIRRORS* entries for source code mirrors. These mirrors provide a fall-back path in case the upstream source specified in *SRC\_URI* within recipes is unavailable.

This class is enabled by default since it is inherited by the *base* class.

### 6.6.85 module

The *module* class provides support for building out-of-tree Linux kernel modules. The class inherits the *module-base* and *kernel-module-split* classes, and implements the *do\_compile* and *do\_install* tasks. The class provides everything needed to build and package a kernel module.

For general information on out-of-tree Linux kernel modules, see the "*Incorporating Out-of-Tree Modules*" section in the Yocto Project Linux Kernel Development Manual.

### 6.6.86 module-base

The *module-base* class provides the base functionality for building Linux kernel modules. Typically, a recipe that builds software that includes one or more kernel modules and has its own means of building the module inherits this class as opposed to inheriting the *module* class.

### 6.6.87 module-rust

The *module-rust* class provides support for building out-of-tree Linux kernel modules written in the Rust programming language. The class inherits the *module* class.

For general information on out-of-tree Linux kernel modules, see the "*Incorporating Out-of-Tree Modules*" section in the Yocto Project Linux Kernel Development Manual.

### 6.6.88 multilib\*

The *multilib\** classes provide support for building libraries with different target optimizations or target architectures and installing them side-by-side in the same image.

For more information on using the Multilib feature, see the "*Combining Multiple Versions of Library Files into One Image*" section in the Yocto Project Development Tasks Manual.

### 6.6.89 native

The *native* class provides common functionality for recipes that build tools to run on the *Build Host* (i.e. tools that use the compiler or other tools from the build host).

You can create a recipe that builds tools that run natively on the host a couple different ways:

- Create a `myrecipe-native.bb` recipe that inherits the *native* class. If you use this method, you must order the `inherit` statement in the recipe after all other `inherit` statements so that the *native* class is inherited last.

#### Nota

When creating a recipe this way, the recipe name must follow this naming convention:

```
myrecipe-native.bb
```

Not using this naming convention can lead to subtle problems caused by existing code that depends on that naming convention.

- Or, create a *native* variant of any target recipe (e.g. `myrecipe.bb`) by adding the following to the recipe:

```
BBCLASSEXTEND = "native"
```

Inside the recipe, use `:class-native` and `:class-target` overrides to specify any functionality specific to the respective native or target case.

Although applied differently, the *native* class is used with both methods. The advantage of the second method is that you do not need to have two separate recipes (assuming you need both) for native and target. All common parts of the recipe are automatically shared.

### 6.6.90 nativesdk

The *nativesdk* class provides common functionality for recipes that wish to build tools to run as part of an SDK (i.e. tools that run on *SDKMACHINE*).

You can create a recipe that builds tools that run on the SDK machine a couple different ways:

- Create a `nativesdk-myrecipe.bb` recipe that inherits the *nativesdk* class. If you use this method, you must order the inherit statement in the recipe after all other inherit statements so that the *nativesdk* class is inherited last.

#### Nota

When creating a recipe, you must follow this naming convention:

```
nativesdk-myrecipe.bb
```

Not doing so can lead to subtle problems because there is code that depends on the naming convention.

- Or, create a *nativesdk* variant of any target recipe (e.g. `myrecipe.bb`) by adding the following to the recipe:

```
BBCLASSEXTEND = "nativesdk"
```

Inside the recipe, use `:class-nativesdk` and `:class-target` overrides to specify any functionality specific to the respective SDK machine or target case.

Although applied differently, the *nativesdk* class is used with both methods. The advantage of the second method is that you do not need to have two separate recipes (assuming you need both) for the SDK machine and the target. All common parts of the recipe are automatically shared.

### 6.6.91 nopackages

Disables packaging tasks for those recipes and classes where packaging is not needed.

### 6.6.92 nospdx

The *nospdx* allows a recipe to opt out of SPDX generation provided by *create-spdx*.

### 6.6.93 npm

#### ⚠ Avvertimento

The NPM fetcher is currently disabled due to security concerns. See [355cd22](#) for more information.

Provides support for building Node.js software fetched using the [node package manager \(NPM\)](#).

#### ℹ Nota

Currently, recipes inheriting this class must use the `npm://` fetcher to have dependencies fetched and packaged automatically.

For information on how to create NPM packages, see the "[Creating Node Package Manager \(NPM\) Packages](#)" section in the Yocto Project Development Tasks Manual.

### 6.6.94 overlayfs

It's often desired in Embedded System design to have a read-only root filesystem. But a lot of different applications might want to have read-write access to some parts of a filesystem. It can be especially useful when your update mechanism overwrites the whole root filesystem, but you may want your application data to be preserved between updates. The [overlayfs](#) class provides a way to achieve that by means of `overlayfs` and at the same time keeping the base root filesystem read-only.

To use this class, set a mount point for a partition `overlayfs` is going to use as upper layer in your machine configuration. The underlying file system can be anything that is supported by `overlayfs`. This has to be done in your machine configuration:

```
OVERLAYFS_MOUNT_POINT[data] = "/data"
```

#### ℹ Nota

- QA checks fail to catch file existence if you redefine this variable in your recipe!
- Only the existence of the systemd mount unit file is checked, not its contents.
- To get more details on `overlayfs`, its internals and supported operations, please refer to the official documentation of the [Linux kernel](#).

The class assumes you have a `data.mount` systemd unit defined elsewhere in your BSP (e.g. in `systemd-machine-units` recipe) and it's installed into the image.

Then you can specify writable directories on a recipe basis (e.g. in `my-application.bb`):

```
OVERLAYFS_WRITABLE_PATHS[data] = "/usr/share/my-custom-application"
```

To support several mount points you can use a different variable flag. Assuming we want to have a writable location on the file system, but do not need that the data survives a reboot, then we could have a `mnt-overlay.mount` unit for a `tmpfs` file system.

In your machine configuration:

```
OVERLAYFS_MOUNT_POINT[mnt-overlay] = "/mnt/overlay"
```

and then in your recipe:

```
OVERLAYFS_WRITABLE_PATHS[mnt-overlay] = "/usr/share/another-application"
```

On a practical note, your application recipe might require multiple overlays to be mounted before running to avoid writing to the underlying file system (which can be forbidden in case of read-only file system). To achieve that *overlayfs* provides a `systemd` helper service for mounting overlays. This helper service is named `${PN}-overlays.service` and can be depended on in your application recipe (named `application` in the following example) `systemd` unit by adding to the unit the following:

```
[Unit]
After=application-overlays.service
Requires=application-overlays.service
```

#### Nota

The class does not support the `/etc` directory itself, because `systemd` depends on it. In order to get `/etc` in overlays, see *overlayfs-etc*.

## 6.6.95 overlayfs-etc

In order to have the `/etc` directory in `overlayfs` a special handling at early boot stage is required. The idea is to supply a custom init script that mounts `/etc` before launching the actual init program, because the latter already requires `/etc` to be mounted.

Example usage in image recipe:

```
IMAGE_FEATURES += "overlayfs-etc"
```

#### Nota

This class must not be inherited directly. Use *IMAGE\_FEATURES* or *EXTRA\_IMAGE\_FEATURES*

Your machine configuration should define at least the device, mount point, and file system type you are going to use for `overlayfs`:



```
OVERLAYFS_ETC_MOUNT_POINT = "/data"
OVERLAYFS_ETC_DEVICE = "/dev/mmcblk0p2"
OVERLAYFS_ETC_FSTYPE ?= "ext4"
```

To control more mount options you should consider setting mount options (defaults is used by default):

```
OVERLAYFS_ETC_MOUNT_OPTIONS = "wsync"
```

The class provides two options for `/sbin/init` generation:

- The default option is to rename the original `/sbin/init` to `/sbin/init.orig` and place the generated init under original name, i.e. `/sbin/init`. It has an advantage that you won't need to change any kernel parameters in order to make it work, but it poses a restriction that package-management can't be used, because updating the init manager would remove the generated script.
- If you wish to keep original init as is, you can set:

```
OVERLAYFS_ETC_USE_ORIG_INIT_NAME = "0"
```

Then the generated init will be named `/sbin/preinit` and you would need to extend your kernel parameters manually in your bootloader configuration.

## 6.6.96 own-mirrors

The *own-mirrors* class makes it easier to set up your own *PREMIRRORS* from which to first fetch source before attempting to fetch it from the upstream specified in *SRC\_URI* within each recipe.

To use this class, inherit it globally and specify *SOURCE\_MIRROR\_URL*. Here is an example:

```
INHERIT += "own-mirrors"
SOURCE_MIRROR_URL = "http://example.com/my-source-mirror"
```

You can specify only a single URL in *SOURCE\_MIRROR\_URL*.

## 6.6.97 package

The *package* class supports generating packages from a build's output. The core generic functionality is in `package.bbclass`. The code specific to particular package types resides in these package-specific classes: *package\_deb*, *package\_rpm*, *package\_ipk*.

You can control the list of resulting package formats by setting the *PACKAGE\_CLASSES* variable in your *build/conf/local.conf* file or distro *configuration file*. When defining the variable, you can specify one or more package types. Since images are generated from packages, a packaging class is needed to enable image generation. The first class listed in this variable is used for image generation.

If you take the optional step to set up a repository (package feed) on the development host that can be used by DNF, you can install packages from the feed while you are running the image on the target (i.e. runtime installation of packages). For more information, see the "*Using Runtime Package Management*" section in the Yocto Project Development Tasks Manual.

The package-specific class you choose can affect build-time performance and has space ramifications. In general, building a package with IPK takes about thirty percent less time as compared to using RPM to build the same or similar package. This comparison takes into account a complete build of the package with all dependencies previously built. The reason for this discrepancy is because the RPM package manager creates and processes more *Metadata* than the IPK package manager. Consequently, you might consider setting *PACKAGE\_CLASSES* to "*package\_ipk*" if you are building smaller systems.

Before making your package manager decision, however, you should consider some further things about using RPM:

- RPM starts to provide more abilities than IPK due to the fact that it processes more Metadata. For example, this information includes individual file types, file checksum generation and evaluation on install, sparse file support, conflict detection and resolution for Multilib systems, ACID style upgrade, and repackaging abilities for rollbacks.
- For smaller systems, the extra space used for the Berkeley Database and the amount of metadata when using RPM can affect your ability to perform on-device upgrades.

You can find additional information on the effects of the package class at this Yocto Project mailing list link: <https://lists.yoctoproject.org/g/poky/topic/61292484#msg6286>

### 6.6.98 *package\_deb*

The *package\_deb* class provides support for creating packages that use the Debian (i.e. *.deb*) file format. The class ensures the packages are written out in a *.deb* file format to the  $\${DEPLOY\_DIR\_DEB}$  directory.

This class inherits the *package* class and is enabled through the *PACKAGE\_CLASSES* variable.

### 6.6.99 *package\_ipk*

The *package\_ipk* class provides support for creating packages that use the IPK (i.e. *.ipk*) file format. The class ensures the packages are written out in a *.ipk* file format to the  $\${DEPLOY\_DIR\_IPK}$  directory.

This class inherits the *package* class and is enabled through the *PACKAGE\_CLASSES* variable.

### 6.6.100 *package\_rpm*

The *package\_rpm* class provides support for creating packages that use the RPM (i.e. *.rpm*) file format. The class ensures the packages are written out in a *.rpm* file format to the  $\${DEPLOY\_DIR\_RPM}$  directory.

This class inherits the *package* class and is enabled through the *PACKAGE\_CLASSES* variable.

### 6.6.101 *packagedata*

The *packagedata* class provides common functionality for reading *pkgdata* files found in *PKGDATA\_DIR*. These files contain information about each output package produced by the OpenEmbedded build system.

This class is enabled by default because it is inherited by the *package* class.

### 6.6.102 packagegroup

The *packagegroup* class sets default values appropriate for package group recipes (e.g. *PACKAGES*, *PACKAGE\_ARCH*, *ALLOW\_EMPTY*, and so forth). It is highly recommended that all package group recipes inherit this class.

For information on how to use this class, see the "*Customizing Images Using Custom Package Groups*" section in the Yocto Project Development Tasks Manual.

Previously, this class was called the `task` class.

#### Nota

If you're defining a packagegroup and need to set:

```
PACKAGE_ARCH = "${MACHINE_ARCH}"
```

for the packagegroup, you need to do that *before* the `inherit packagegroup` line in the recipe file. Setting it afterward can break BitBake parsing, result in an "allarch" architecture mismatch error, or allow architecture-independent defaults to override your intent.

### 6.6.103 patch

The *patch* class provides all functionality for applying patches during the *do\_patch* task.

This class is enabled by default because it is inherited by the *base* class.

### 6.6.104 perlnative

When inherited by a recipe, the *perlnative* class supports using the native version of Perl built by the build system rather than using the version provided by the build host.

### 6.6.105 pypi

The *pypi* class sets variables appropriately for recipes that build Python modules from *PyPI*, the Python Package Index. By default it determines the PyPI package name based upon *BPN* (stripping the "python-" or "python3-" prefix off if present), however in some cases you may need to set it manually in the recipe by setting *PYPI\_PACKAGE*.

Variables set by the *pypi* class include *SRC\_URI*, *SECTION*, *HOMEPAGE*, *UPSTREAM\_CHECK\_URI*, *UPSTREAM\_CHECK\_REGEX* and *CVE\_PRODUCT*.

### 6.6.106 python\_flit\_core

The *python\_flit\_core* class enables building Python modules which declare the *PEP-517* compliant *flit\_core*. *buildapi* build-backend in the `[build-system]` section of `pyproject.toml` (See *PEP-518*).

Python modules built with `flit_core.buildapi` are pure Python (no C or Rust extensions).

Internally this uses the *python\_pep517* class.

### 6.6.107 `python_maturin`

The `python_maturin` class provides support for python-maturin, a replacement for `setuptools_rust` and another "backend" for building Python Wheels.

### 6.6.108 `python_mesonpy`

The `python_mesonpy` class enables building Python modules which use the meson-python build system.

Internally this uses the `python_pep517` class.

### 6.6.109 `python_pbr`

The `python_pbr` class enables building Python projects which use the [Python Build Reasonableness](#) backend.

This class adds `python3-pbr-native` to the recipe's build-time dependencies.

Internally this uses the `python_pep517` class.

### 6.6.110 `python_pdm`

The `python_pdm` class adds support for building Python packages with the [PDM](#) package and dependency manager.

This class adds `python3-pdm-backend-native` to the recipe's build-time dependencies.

Internally this uses the `python_pep517` class.

### 6.6.111 `python_pep517`

The `python_pep517` class builds and installs a Python `wheel` binary archive (see [PEP-517](#)).

Recipes wouldn't inherit this directly, instead typically another class will inherit this and add the relevant native dependencies.

Examples of classes which do this are `python_flit_core`, `python_setuptools_build_meta`, and `python_poetry_core`.

### 6.6.112 `python_poetry_core`

The `python_poetry_core` class enables building Python modules which use the [Poetry Core](#) build system.

Internally this uses the `python_pep517` class.

### 6.6.113 `python_py3`

The `python_py3` class helps make sure that Python extensions written in Rust and built with [PyO3](#), properly set up the environment for cross compilation.

This class is internal to the `python-setuptools3_rust` class and is not meant to be used directly in recipes.

### 6.6.114 `python_uv_build`

The `python_uv_build` class can be inherited in Python recipes that are built with `uv_build` and which are [PEP-517](#) compliant.

### 6.6.115 `python-setuptools3_rust`

The `python-setuptools3_rust` class enables building Python extensions implemented in Rust with [PyO3](#), which allows to compile and distribute Python extensions written in Rust as easily as if they were written in C.

This class inherits the `setuptools3` and `python_pyo3` classes.

### 6.6.116 `pixbufcache`

The `pixbufcache` class generates the proper post-install and post-remove (postinst/postrm) scriptlets for packages that install pixbuf loaders, which are used with `gdk-pixbuf`. These scriptlets call `update_pixbuf_cache` to add the pixbuf loaders to the cache. Since the cache files are architecture-specific, `update_pixbuf_cache` is run using QEMU if the postinst scriptlets need to be run on the build host during image creation.

If the pixbuf loaders being installed are in packages other than the recipe's main package, set `PIXBUF_PACKAGES` to specify the packages containing the loaders.

### 6.6.117 `pkgconfig`

The `pkgconfig` class provides a standard way to get header and library information by using `pkg-config`. This class aims to smooth integration of `pkg-config` into libraries that use it.

During staging, BitBake installs `pkg-config` data into the `sysroots/` directory. By making use of `sysroot` functionality within `pkg-config`, the `pkgconfig` class no longer has to manipulate the files.

### 6.6.118 `populate_sdk`

The `populate_sdk` class provides support for SDK-only recipes. For information on advantages gained when building a cross-development toolchain using the `do_populate_sdk` task, see the "[Building an SDK Installer](#)" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### 6.6.119 `populate_sdk_*`

The `populate_sdk_*` classes support SDK creation and consist of the following classes:

- `populate_sdk_base`: The base class supporting SDK creation under all package managers (i.e. DEB, RPM, and opkg).
- `populate_sdk_deb`: Supports creation of the SDK given the Debian package manager.
- `populate_sdk_rpm`: Supports creation of the SDK given the RPM package manager.
- `populate_sdk_ipk`: Supports creation of the SDK given the opkg (IPK format) package manager.
- `populate_sdk_ext`: Supports extensible SDK creation under all package managers.

The `populate_sdk_base` class inherits the appropriate `populate_sdk_*` (i.e. `deb`, `rpm`, and `ipk`) based on `IMAGE_PKGTYPE`.

The base class ensures all source and destination directories are established and then populates the SDK. After populating the SDK, the `populate_sdk_base` class constructs two sysroots: `${SDK_ARCH}-nativesdk`, which contains the cross-compiler and associated tooling, and the target, which contains a target root filesystem that is configured for the SDK usage. These two images reside in `SDK_OUTPUT`, which consists of the following:

```
${SDK_OUTPUT}/${SDK_ARCH}-nativesdk-pkgs
${SDK_OUTPUT}/${SDKTARGETSYSROOT}/target-pkgs
```

Finally, the base populate SDK class creates the toolchain environment setup script, the tarball of the SDK, and the installer.

The respective `populate_sdk_deb`, `populate_sdk_rpm`, and `populate_sdk_ipk` classes each support the specific type of SDK. These classes are inherited by and used with the `populate_sdk_base` class.

For more information on the cross-development toolchain generation, see the "*Generazione di Toolchain di Cross-Sviluppo*" section in the Yocto Project Overview and Concepts Manual. For information on advantages gained when building a cross-development toolchain using the `do_populate_sdk` task, see the "*Building an SDK Installer*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### 6.6.120 prexport

The `prexport` class provides functionality for exporting *PR* values.

#### Nota

This class is not intended to be used directly. Rather, it is enabled when using "bitbake-prserv-tool export".

### 6.6.121 primport

The `primport` class provides functionality for importing *PR* values.

#### Nota

This class is not intended to be used directly. Rather, it is enabled when using "bitbake-prserv-tool import".

### 6.6.122 prserv

The `prserv` class provides functionality for using a *PR service* in order to automatically manage the incrementing of the *PR* variable for each recipe.

This class is enabled by default because it is inherited by the `package` class. However, the OpenEmbedded build system will not enable the functionality of this class unless `PRSERV_HOST` has been set.

### 6.6.123 `pptest`

The `pptest` class provides functionality for packaging and installing runtime tests for recipes that build software that provides these tests.

This class is intended to be inherited by individual recipes. However, the class' functionality is largely disabled unless "pptest" appears in `DISTRO_FEATURES`. See the "*Testing Packages With pptest*" section in the Yocto Project Test Environment Manual for more information on pptest.

### 6.6.124 `pptest-cargo`

The `pptest-cargo` class is a class which extends the `cargo` class and adds `compile_pptest_cargo` and `install_pptest_cargo` steps to respectively build and install test suites defined in the `Cargo.toml` file, into a dedicated `-pptest` package.

### 6.6.125 `pptest-gnome`

Enables package tests (ptests) specifically for GNOME packages, which have tests intended to be executed with `gnome-desktop-testing`.

For information on setting up and running ptests, see the "*Testing Packages With pptest*" section in the Yocto Project Test Environment Manual.

### 6.6.126 `pptest-python-pytest`

The `pptest-python-pytest` class can be inherited in Python-based recipes to automatically configure the `pptest` class for Python packages leveraging the `pytest` unit test framework.

Within the recipe, the `PTEST_PYTEST_DIR` variable specifies the path to the directory containing the tests that will be installed in `D` by the `do_install_pptest_base` task, as well as a specific `run-pptest` script for this task.

### 6.6.127 `python3-dir`

The `python3-dir` class provides the base version, location, and site package location for Python 3.

### 6.6.128 `python3native`

The `python3native` class supports using the native version of Python 3 built by the build system rather than support of the version provided by the build host.

### 6.6.129 `python3targetconfig`

The `python3targetconfig` class supports using the native version of Python 3 built by the build system rather than support of the version provided by the build host, except that the configuration for the target machine is accessible (such as correct installation directories). This also adds a dependency on target `python3`, so should only be used where appropriate in order to avoid unnecessarily lengthening builds.

### 6.6.130 `qemu`

The *qemu* class provides functionality for recipes that either need QEMU or test for the existence of QEMU. Typically, this class is used to run programs for a target system on the build host using QEMU's application emulation mode.

### 6.6.131 `recipe_sanity`

The *recipe\_sanity* class checks for the presence of any host system recipe prerequisites that might affect the build (e.g. variables that are set or software that is present).

### 6.6.132 `relative_symlinks`

The *relative\_symlinks* class walks the symbolic links in the *D* directory and replaces links pointing to absolute paths to relative paths. This is occasionally used in some recipes that create wrong symbolic links when their *native* version is built, and/or would cause breakage in the *Cache di Shared State*.

For example, if the following symbolic link is found in *D*:

```
/usr/bin/foo -> /sbin/bar
```

It is replaced by:

```
/usr/bin/foo -> ../../sbin/bar
```

### 6.6.133 `relocatable`

The *relocatable* class enables relocation of binaries when they are installed into the sysroot.

This class makes use of the *chroot* class and is used by both the *cross* and *native* classes.

### 6.6.134 `remove-libtool`

The *remove-libtool* class adds a post function to the *do\_install* task to remove all *.la* files installed by *libtool*. Removing these files results in them being absent from both the sysroot and target packages.

If a recipe needs the *.la* files to be installed, then the recipe can override the removal by setting *REMOVE\_LIBTOOL\_LA* to "0" as follows:

```
REMOVE_LIBTOOL_LA = "0"
```



**i Nota**

The *remove-libtool* class is not enabled by default.

**6.6.135 report-error**

The *report-error* class supports enabling the *error reporting tool*", which allows you to submit build error information to a central database.

The class collects debug information for recipe, recipe version, task, machine, distro, build system, target system, host distro, branch, commit, and log. From the information, report files using a JSON format are created and stored in `${LOG_DIR}/error-report`.

**6.6.136 retain**

The *retain* class can be used to create a tarball of the work directory for a recipe when one of its tasks fails, or any other nominated directories. It is useful in cases where the environment in which builds are run is ephemeral or otherwise inaccessible for examination during debugging.

To enable, add the following to your configuration:

```
INHERIT += "retain"
```

The class can be disabled for specific recipes using the *RETAIN\_ENABLED* variable.

**6.6.137 rm\_work**

The *rm\_work* class supports deletion of temporary workspace, which can ease your hard drive demands during builds.

The OpenEmbedded build system can use a substantial amount of disk space during the build process. A portion of this space is the work files under the `${TMPDIR}/work` directory for each recipe. Once the build system generates the packages for a recipe, the work files for that recipe are no longer needed. However, by default, the build system preserves these files for inspection and possible debugging purposes. If you would rather have these files deleted to save disk space as the build progresses, you can enable *rm\_work* by adding the following to your *build/conf/local.conf* file, which is found in the *Build Directory*:

```
INHERIT += "rm_work"
```

If you are modifying and building source code out of the work directory for a recipe, enabling *rm\_work* will potentially result in your changes to the source being lost. To exclude some recipes from having their work directories deleted by *rm\_work*, you can add the names of the recipe or recipes you are working on to the *RM\_WORK\_EXCLUDE* variable, which can also be set in your *build/conf/local.conf* file. Here is an example:

```
RM_WORK_EXCLUDE += "busybox glibc"
```

Finally, if you are using this class for a recipe but want to prevent *BitBake* from deleting specific folders or files in that recipe's *WORKDIR* (other than `temp`), you can preserve those folders or files with the *RM\_WORK\_EXCLUDE\_ITEMS* variable as follows:

```
RM_WORK_EXCLUDE_ITEMS += "items_to_keep"
```

### 6.6.138 `rootfs*`

The `rootfs*` classes support creating the root filesystem for an image and consist of the following classes:

- The `rootfs-postcommands` class, which defines filesystem post-processing functions for image recipes.
- The `rootfs_deb` class, which supports creation of root filesystems for images built using `.deb` packages.
- The `rootfs_rpm` class, which supports creation of root filesystems for images built using `.rpm` packages.
- The `rootfs_ipk` class, which supports creation of root filesystems for images built using `.ipk` packages.
- The `rootfsdebugfiles` class, which installs additional files found on the build host directly into the root filesystem.

The root filesystem is created from packages using one of the `rootfs*` files as determined by the `PACKAGE_CLASSES` variable.

For information on how root filesystem images are created, see the "*Generazione dell'Immagine*" section in the Yocto Project Overview and Concepts Manual.

### 6.6.139 `rust`

The `rust` class is an internal class which is just used in the "rust" recipe, to build the Rust compiler and runtime library. Except for this recipe, it is not intended to be used directly.

### 6.6.140 `rust-common`

The `rust-common` class is an internal class to the `cargo_common` and `rust` classes and is not intended to be used directly.

### 6.6.141 `rust-target-config`

The `rust-target-config` class is an internal class to the `cargo_common` and `rust` classes and is not intended to be used directly.

It is used to generate a JSON specification file from the features listed in `TUNE_FEATURES`, which is used for cross-compiling. The logic is done in a `do_rust_gen_targets` task.

### 6.6.142 `sanity`

The `sanity` class checks to see if prerequisite software is present on the host system so that users can be notified of potential problems that might affect their build. The class also performs basic user configuration checks from the `build/conf/local.conf` configuration file to prevent common mistakes that cause build failures. Distribution policy usually determines whether to include this class.

### 6.6.143 sbom-cve-check

The *sbom-cve-check* class uses the *sbom-cve-check* command-line tool for post-build CVE analysis. It relies on the *create-spdx* class as SPDX files are the input of this tool.

This class should be enabled through the *core/yocto/sbom-cve-check* fragment:

```
$ bitbake-config-build enable-fragment core/yocto/sbom-cve-check
```

After building an image, *sbom-cve-check* will generate one or more reports in the *DEPLOY\_DIR\_IMAGE* directory depending on the current value of *SBOM\_CVE\_CHECK\_EXPORT\_VARS*.

See the variables starting with *SBOM\_CVE\_CHECK\_* in the *Yocto Project Reference Manual glossary* to learn more on how to configure the behavior of this class.

### 6.6.144 sbom-cve-check-recipe

The *sbom-cve-check-recipe* class uses the *sbom-cve-check* command-line tool for post-build CVE analysis of a recipe. It relies on the *create-spdx* class as SPDX files are the input of this tool.

This class can be inherited in any recipe. Compared to the *ref-classes-sbom-cve-check* class, this class only uses the SBOM of the recipe (after the *create\_recipe\_sbom* task is run) to determine which is the underlying software and do the analysis, meaning that building the recipe itself isn't necessary.

To use this class, inherit it in the recipe and run:

```
$ bitbake <recipe> -c sbom_cve_check_recipe
```

After running the command, *sbom-cve-check* will generate one or more reports in the *DEPLOY\_DIR\_IMAGE* directory depending on the current value of *SBOM\_CVE\_CHECK\_EXPORT\_VARS*.

See the variables starting with *SBOM\_CVE\_CHECK\_* in the *Yocto Project Reference Manual glossary* to learn more on how to configure the behavior of this class.

### 6.6.145 scons

The *scons* class supports recipes that need to build software that uses the SCons build system. You can use the *EXTRA\_OESCONS* variable to specify additional configuration options you want to pass SCons command line.

### 6.6.146 sdl

The *sdl* class supports recipes that need to build software that uses the Simple DirectMedia Layer (SDL) library.

### 6.6.147 python\_setuptools\_build\_meta

The *python\_setuptools\_build\_meta* class enables building Python modules which declare the *PEP-517* compliant *setuptools.build\_meta* build-backend in the *[build-system]* section of *pyproject.toml* (See *PEP-518*).

Python modules built with *setuptools.build\_meta* can be pure Python or include C or Rust extensions).

Internally this uses the *python\_pep517* class.

### 6.6.148 `setuptools3`

The `setuptools3` class supports Python version 3.x extensions that use build systems based on `setuptools` (e.g. only have a `setup.py` and have not migrated to the official `pyproject.toml` format). If your recipe uses these build systems, the recipe needs to inherit the `setuptools3` class.

#### Nota

The `setuptools3` class `do_compile` task now calls `setup.py bdist_wheel` to build the wheel binary archive format (See [PEP-427](#)).

A consequence of this is that legacy software still using deprecated `distutils` from the Python standard library cannot be packaged as wheels. A common solution is to replace `from distutils.core import setup` with `from setuptools import setup`.

#### Nota

The `setuptools3` class `do_install` task now installs the wheel binary archive. In current versions of `setuptools` the legacy `setup.py install` method is deprecated. If the `setup.py` cannot be used with wheels, for example it creates files outside of the Python module or standard entry points, then `setuptools3_legacy` should be used.

### 6.6.149 `setuptools3_legacy`

The `setuptools3_legacy` class supports Python version 3.x extensions that use build systems based on `setuptools` (e.g. only have a `setup.py` and have not migrated to the official `pyproject.toml` format). Unlike `setuptools3`, this uses the traditional `setup.py build` and `install` commands and not wheels. This use of `setuptools` like this is [deprecated](#) but still relatively common.

### 6.6.150 `setuptools3-base`

The `setuptools3-base` class provides a reusable base for other classes that support building Python version 3.x extensions. If you need functionality that is not provided by the `setuptools3` class, you may want to inherit `setuptools3-base`. Some recipes do not need the tasks in the `setuptools3` class and inherit this class instead.

### 6.6.151 `sign_rpm`

The `sign_rpm` class supports generating signed RPM packages.

### 6.6.152 `siteinfo`

The `siteinfo` class provides information about the targets that might be needed by other classes or recipes.

As an example, consider Autotools, which can require tests that must execute on the target hardware. Since this is not possible in general when cross compiling, site information is used to provide cached test results so these tests can be skipped over but still make the correct values available. The `meta/site` directory contains test results sorted

into different categories such as architecture, endianness, and the `libc` used. Site information provides a list of files containing data relevant to the current build in the `CONFIG_SITE` variable that Autotools automatically picks up.

The class also provides variables like `SITEINFO_ENDIANNES` and `SITEINFO_BITS` that can be used elsewhere in the metadata.

### 6.6.153 sstate

The `sstate` class provides support for Shared State (sstate). By default, the class is enabled through the `INHERIT_DISTRO` variable's default value.

For more information on sstate, see the "*Cache di Shared State*" section in the Yocto Project Overview and Concepts Manual.

### 6.6.154 staging

The `staging` class installs files into individual recipe work directories for sysroots. The class contains the following key tasks:

- The `do_populate_sysroot` task, which is responsible for handing the files that end up in the recipe sysroots.
- The `do_prepare_recipe_sysroot` task (a "partner" task to the `populate_sysroot` task), which installs the files into the individual recipe work directories (i.e. `WORKDIR`).

The code in the `staging` class is complex and basically works in two stages:

- *Stage One:* The first stage addresses recipes that have files they want to share with other recipes that have dependencies on the originating recipe. Normally these dependencies are installed through the `do_install` task into `${D}`. The `do_populate_sysroot` task copies a subset of these files into `${SYSROOT_DESTDIR}`. This subset of files is controlled by the `SYSROOT_DIRS`, `SYSROOT_DIRS_NATIVE`, and `SYSROOT_DIRS_IGNORE` variables.

#### Nota

Additionally, a recipe can customize the files further by declaring a processing function in the `SYSROOT_PREPROCESS_FUNCS` variable.

A shared state (sstate) object is built from these files and the files are placed into a subdirectory of `build/tmp/sysroots-components/`. The files are scanned for hardcoded paths to the original installation location. If the location is found in text files, the hardcoded locations are replaced by tokens and a list of the files needing such replacements is created. These adjustments are referred to as "FIXMEs". The list of files that are scanned for paths is controlled by the `SSTATE_SCAN_FILES` variable.

- *Stage Two:* The second stage addresses recipes that want to use something from another recipe and declare a dependency on that recipe through the `DEPENDS` variable. The recipe will have a `do_prepare_recipe_sysroot` task and when this task executes, it creates the `recipe-sysroot` and `recipe-sysroot-native` in the recipe work directory (i.e. `WORKDIR`). The OpenEmbedded build system creates hard links to copies of the relevant files from `sysroots-components` into the recipe work directory.

**i Nota**

If hard links are not possible, the build system uses actual copies.

The build system then addresses any "FIXMEs" to paths as defined from the list created in the first stage.

Finally, any files in `${bindir}` within the sysroot that have the prefix "postinst-" are executed.

**i Nota**

Although such sysroot post installation scripts are not recommended for general use, the files do allow some issues such as user creation and module indexes to be addressed.

Because recipes can have other dependencies outside of *DEPENDS* (e.g. `do_unpack[depends] += "tar-native:do_populate_sysroot"`), the sysroot creation function `extend_recipe_sysroot` is also added as a pre-function for those tasks whose dependencies are not through *DEPENDS* but operate similarly.

When installing dependencies into the sysroot, the code traverses the dependency graph and processes dependencies in exactly the same way as the dependencies would or would not be when installed from sstate. This processing means, for example, a native tool would have its native dependencies added but a target library would not have its dependencies traversed or installed. The same sstate dependency code is used so that builds should be identical regardless of whether sstate was used or not. For a closer look, see the `setscene_depvalid()` function in the *sstate* class.

The build system is careful to maintain manifests of the files it installs so that any given dependency can be installed as needed. The sstate hash of the installed item is also stored so that if it changes, the build system can reinstall it.

### 6.6.155 syslinux

The *syslinux* class provides syslinux-specific functions for building bootable images.

The class supports the following variables:

- *INITRD*: Indicates list of filesystem images to concatenate and use as an initial RAM disk (initrd). This variable is optional.
- *ROOTFS*: Indicates a filesystem image to include as the root filesystem. This variable is optional.
- *AUTO\_SYSLINUXMENU*: Enables creating an automatic menu when set to "1".
- *LABELS*: Lists targets for automatic configuration.
- *APPEND*: Lists append string overrides for each label.
- *SYSINUX\_OPTS*: Lists additional options to add to the syslinux file. Semicolon characters separate multiple options.
- *SYSINUX\_SPLASH*: Lists a background for the VGA boot menu when you are using the boot menu.
- *SYSINUX\_DEFAULT\_CONSOLE*: Set to "console=ttyX" to change kernel boot default console.

- `SYSLINUX_SERIAL`: Sets an alternate serial port. Or, turns off serial when the variable is set with an empty string.
- `SYSLINUX_SERIAL_TTY`: Sets an alternate "console=tty..." kernel boot argument.

### 6.6.156 systemd

The `systemd` class provides support for recipes that install systemd unit files.

The functionality for this class is disabled unless you have "systemd" in `DISTRO_FEATURES`.

Under this class, the recipe or Makefile (i.e. whatever the recipe is calling during the `do_install` task) installs unit files into `${D}${systemd_unitdir}/system`. If the unit files being installed go into packages other than the main package, you need to set `SYSTEMD_PACKAGES` in your recipe to identify the packages in which the files will be installed.

You should set `SYSTEMD_SERVICE` to the name of the service file. You should also use a package name override to indicate the package to which the value applies. If the value applies to the recipe's main package, use `${PN}`. Here is an example from the `connman` recipe:

```
SYSTEMD_SERVICE:${PN} = "connman.service"
```

Services are set up to start on boot automatically unless you have set `SYSTEMD_AUTO_ENABLE` to "disable".

For more information on `systemd`, see the "*Selecting an Initialization Manager*" section in the Yocto Project Development Tasks Manual.

### 6.6.157 systemd-boot

The `systemd-boot` class provides functions specific to the systemd-boot bootloader for building bootable images. This is an internal class and is not intended to be used directly.

#### Nota

The `systemd-boot` class is a result from merging the `gummiboot` class used in previous Yocto Project releases with the `systemd` project.

Set the `EFI_PROVIDER` variable to "`systemd-boot`" to use this class. Doing so creates a standalone EFI bootloader that is not dependent on systemd.

For information on more variables used and supported in this class, see the `SYSTEMD_BOOT_CFG`, `SYSTEMD_BOOT_ENTRIES`, and `SYSTEMD_BOOT_TIMEOUT` variables.

You can also see the [Systemd-boot documentation](#) for more information.

### 6.6.158 terminal

The `terminal` class provides support for starting a terminal session. The `OE_TERMINAL` variable controls which terminal emulator is used for the session.

Other classes use the `terminal` class anywhere a separate terminal session needs to be started. For example, the `patch` class assuming `PATCHRESOLVE` is set to "user", the `cm11` class, and the `devshell` class all use the `terminal` class.

### 6.6.159 `testexport`

Based on the `testimage` class, the `testexport` class can be used to export the test environment outside of the *OpenEmbedded Build System*. This will generate the directory structure to execute the runtime tests using the `runexported.py` Python script.

For more details on how to use `testexport`, see the *Exporting Tests* section in the Yocto Project Test Environment Manual.

### 6.6.160 `testimage`

The `testimage` class supports running automated tests against images using QEMU and on actual hardware. The classes handle loading the tests and starting the image. To use the classes, you need to perform steps to set up the environment.

To enable this class, add the following to your configuration:

```
IMAGE_CLASSES += "testimage"
```

The tests are commands that run on the target system over `ssh`. Each test is written in Python and makes use of the `unittest` module.

The `testimage` class runs tests on an image when called using the following:

```
$ bitbake -c testimage image
```

Alternatively, if you wish to have tests automatically run for each image after it is built, you can set `TESTIMAGE_AUTO`:

```
TESTIMAGE_AUTO = "1"
```

For information on how to enable, run, and create new tests, see the *"Performing Automated Runtime Testing"* section in the Yocto Project Test Environment Manual.

### 6.6.161 `testsdk`

This class supports running automated tests against software development kits (SDKs). The `testsdk` class runs tests on an SDK when called using the following:

```
$ bitbake -c testsdk image
```

The list of test modules that are run can be controlled with the `TESTSDK_SUITES` variable.



**i Nota**

Best practices include using *IMAGE\_CLASSES* rather than *INHERIT* to inherit the *testsdk* class for automated SDK testing.

**6.6.162 texinfo**

This class should be inherited by recipes whose upstream packages invoke the *texinfo* utilities at build-time. Native and cross recipes are made to use the dummy scripts provided by *texinfo-dummy-native*, for improved performance. Target architecture recipes use the genuine Texinfo utilities. By default, they use the Texinfo utilities on the host system.

**i Nota**

If you want to use the Texinfo recipe shipped with the build system, you can remove "texinfo-native" from *ASSUME\_PROVIDED* and makeinfo from *SANITY\_REQUIRED\_UTILITIES*.

**6.6.163 toaster**

The *toaster* class collects information about packages and images and sends them as events that the BitBake user interface can receive. The class is enabled when the Toaster user interface is running.

This class is not intended to be used directly.

**6.6.164 toolchain-scripts**

The *toolchain-scripts* class provides the scripts used for setting up the environment for installed SDKs.

**6.6.165 toolchain/clang**

The *toolchain/clang* class defines commands for building recipes with Clang/LLVM compiler and utilities.

This class is not meant to be inherited directly. Instead, you should either:

- set the *PREFERRED\_TOOLCHAIN\_TARGET*, *PREFERRED\_TOOLCHAIN\_NATIVE* or *PREFERRED\_TOOLCHAIN\_SDK* variables to "clang" from a *Configuration File*. This will make the *base* class use the *toolchain/clang* accordingly. All recipes will be built with the Clang/LLVM toolchain, exception be made for recipes that override the value of *TOOLCHAIN* or *TOOLCHAIN\_NATIVE* to another value.
- set *TOOLCHAIN* or *TOOLCHAIN\_NATIVE* to "clang" from a recipe when the recipe needs to override the default toolchain set by *PREFERRED\_TOOLCHAIN\_TARGET*, *PREFERRED\_TOOLCHAIN\_NATIVE* or *PREFERRED\_TOOLCHAIN\_SDK*.

**6.6.166 toolchain/clang-native**

The *toolchain/clang-native* class defines commands for building *native* recipes with Clang/LLVM compiler and utilities independently of the build context.

The *toolchain/gcc-native* class defines *BUILD\_CC*, *BUILD\_CXX* and other such variables which are rarely used in recipes. Exception be made for target recipes that need to use the compiler from the build host at some point during the build.

This class should not be inherited directly. It is inherited by the *base* class if *TOOLCHAIN\_NATIVE* is set to "clang".

### 6.6.167 toolchain/gcc

The *toolchain/gcc* class defines commands for building recipes with GCC/Binutils compiler and utilities.

This class is not meant to be inherited directly. Instead, you should either:

- set the *PREFERRED\_TOOLCHAIN\_TARGET*, *PREFERRED\_TOOLCHAIN\_NATIVE* or *PREFERRED\_TOOLCHAIN\_SDK* variables to "gcc" from a *Configuration File*. This will make the *base* class use the *toolchain/gcc* accordingly. All recipes will be built with the GCC/Binutils toolchain, exception be made for recipes that override the value of *TOOLCHAIN* or *TOOLCHAIN\_NATIVE* to another value.
- set *TOOLCHAIN* or *TOOLCHAIN\_NATIVE* to "gcc" from a recipe when the recipe needs to override the default toolchain set by *PREFERRED\_TOOLCHAIN\_TARGET*, *PREFERRED\_TOOLCHAIN\_NATIVE* or *PREFERRED\_TOOLCHAIN\_SDK*.

### 6.6.168 toolchain/gcc-native

The *toolchain/gcc-native* class defines commands for building *native* recipes with GCC/Binutils compiler and utilities independently of the build context.

The *toolchain/gcc-native* class defines *BUILD\_CC*, *BUILD\_CXX* and other such variables which are rarely used in recipes. Exception be made for target recipes that need to use the compiler from the build host at some point during the build.

This class should not be inherited directly. It is inherited by the *base* class if *TOOLCHAIN\_NATIVE* is set to "gcc".

### 6.6.169 typecheck

The *typecheck* class provides support for validating the values of variables set at the configuration level against their defined types. The OpenEmbedded build system allows you to define the type of a variable using the "type" varflag. Here is an example:

```
IMAGE_FEATURES[type] = "list"
```

### 6.6.170 uboot-config

The *uboot-config* class provides support for configuring one or more U-Boot build configurations.

There are three ways to configure the recipe for your machine:

- Using the *UBOOT\_MACHINE* variable (and its companion variable *UBOOT\_BINARY*). For example:

```
UBOOT_MACHINE = "config"
UBOOT_BINARY = "u-boot.bin"
```

- Using *UBOOT\_CONFIG* variables. For example:

```

UBOOT_CONFIG ??= "foo bar"
UBOOT_CONFIG[foo] = "config"
UBOOT_CONFIG[bar] = "config2"

UBOOT_CONFIG_IMAGE_FSTYPES[bar] = "fstype"

UBOOT_CONFIG_BINARY[foo] = "binary"

UBOOT_CONFIG_MAKE_OPTS[foo] = "FOO=1"
UBOOT_CONFIG_MAKE_OPTS[bar] = "BAR=1"

UBOOT_CONFIG_FRAGMENTS[foo] = "foo.fragment"

```

In this example, all possible configurations are selected (`foo` and `bar`), but it is also possible to build only `foo` or `bar` by changing the value of `UBOOT_CONFIG` to include either one or the other. For example:

```

UBOOT_CONFIG = "foo"
UBOOT_CONFIG[foo] = "config"
UBOOT_CONFIG[bar] = "config2"

```

Each build configuration is associated to a variable flag definition of `UBOOT_CONFIG`, and associated changes for each config as defined in the various `UBOOT_CONFIG_*` variables.

- `UBOOT_CONFIG[config]`: defconfig file selected for this build configuration. These files are found in the source tree's `configs` folder of U-Boot.

*This option is mandatory.*

See the documentation of `UBOOT_CONFIG` for more information.

- `UBOOT_CONFIG_IMAGE_FSTYPES[config]`: image types to append to the `IMAGE_FSTYPES` variable for image generation for this build configuration.

This can allow building an extra image format that uses the binary generated by this build configuration.

This option is not mandatory and can be left unspecified if not needed.

See the documentation of `UBOOT_CONFIG_IMAGE_FSTYPES` for more information.

- `UBOOT_CONFIG_BINARY[config]`: binary to select as the one to deploy in `DEPLOY_DIR_IMAGE`. The output of a U-Boot build may be more than one binary, for example:

```

u-boot.bin
u-boot-with-spl.bin

```

Setting the `binary` value to `u-boot-with-spl.bin` will make this binary the one deployed in `DEPLOY_DIR_IMAGE`. It is renamed to include the build configuration name in the process (`foo` or `bar` in the above example).

This option defaults to `UBOOT_BINARY` if not specified.

See the documentation of [UBOOT\\_CONFIG\\_BINARY](#) for more information.

- `UBOOT_CONFIG_MAKE_OPTS[config]`: additional options passed to `make` when configuring and compiling U-Boot for this configuration entry. The options in this entry are added before the options in [UBOOT\\_MAKE\\_OPTS](#).

This option is not mandatory and adds nothing if not specified. If you do not have a make option for a given config, you can simply not set the flag for that config.

See the documentation of [UBOOT\\_CONFIG\\_MAKE\\_OPTS](#) for more information.

- `UBOOT_CONFIG_FRAGMENTS[config]`: additional config fragment(s) from the source tree that is used during `do_configure()` to setup the build. The options in this entry are added before the fragments in [UBOOT\\_FRAGMENTS](#).

This option is not mandatory and adds nothing if not specified. If you do not have a fragment a given config, you can simply not set the flag for that config.

See the documentation of [UBOOT\\_CONFIG\\_FRAGMENTS](#) for more information.

- Or, a legacy method using the [UBOOT\\_CONFIG](#) variable by itself. *This method is being deprecated, see note below.* For example:

```
UBOOT_CONFIG ??= "foo bar"
UBOOT_CONFIG[foo] = "config,images,binary"
UBOOT_CONFIG[bar] = "config2,images2,binary2"
```

In this example, all possible configurations are selected (`foo` and `bar`), but it is also possible to build only `foo` or `bar` by changing the value of [UBOOT\\_CONFIG](#) to include either one or the other.

Each build configuration is associated to a variable flag definition of [UBOOT\\_CONFIG](#), that can take up to three comma-separated options (`config,images,binary`):

- `config`: `defconfig` file selected for this build configuration. These files are found in the source tree's `configs` folder of U-Boot.

*This option is mandatory.*

- `images`: image types to append to the [IMAGE\\_FSTYPES](#) variable for image generation for this build configuration.

This can allow building an extra image format that uses the binary generated by this build configuration.

This option is not mandatory and can be left empty.

- `binary`: binary to select as the one to deploy in [DEPLOY\\_DIR\\_IMAGE](#). The output of a U-Boot build may be more than one binary, for example:

```
u-boot.bin
u-boot-with-spl.bin
```

Setting the `binary` value to `u-boot-with-spl.bin` will make this binary the one deployed in [DEPLOY\\_DIR\\_IMAGE](#). It is renamed to include the build configuration name in the process (`foo` or `bar` in the above example).

This option defaults to `UBOOT_BINARY` if unset.

#### **Nota**

The legacy flow has been deprecated. It is recommended to not use this legacy flow as any future extensions to the control knobs will be not added to this methodology. This functionality will be removed after the wrynose LTS release.

Using `UBOOT_MACHINE` and `UBOOT_CONFIG` at the same time is not possible.

See the `UBOOT_CONFIG` and `UBOOT_MACHINE` variables for additional information.

### 6.6.171 `uboot-extlinux-config`

The `uboot-extlinux-config` class provides support for generating an `extlinux.conf` file part of the [Generic Distro Configuration Concept](#) of U-Boot.

The class can be inherited in a [U-Boot](#) recipe with:

```
inherit uboot-extlinux-config
```

However, the class functionality is disabled by default. To enable it, set the `UBOOT_EXTLINUX` variable to "1" from the U-Boot recipe or from a `bbappend` file:

```
UBOOT_EXTLINUX = "1"
```

In addition to `UBOOT_EXTLINUX`, the `UBOOT_EXTLINUX_ROOT` variable must be set to the `root=` parameter of the [Linux kernel command-line](#). For example, the following would set this value to the second partition of MMC block device 0:

```
UBOOT_EXTLINUX_ROOT = "root=/dev/mmcblk0p2"
```

After building the U-Boot recipe, an `extlinux.conf` is generated and placed in the deployment directory (`DEPLOY_DIR_IMAGE`):

```
tmp/deploy/images/<MACHINE>/extlinux.conf
```

This file can be customized using the variables beginning with `UBOOT_EXTLINUX_` in the [Variables Glossary](#) section of the Yocto Project Reference Manual.

#### **Nota**

Multiple `LABELS` can be specified through the `UBOOT_EXTLINUX_LABELS` variable (i.e. multiple boot entries). Override-style assignment should then be used to specify label-specific properties. See the definition of `UBOOT_EXTLINUX_LABELS` for more information.

 **Suggerimento**

When using the *bootloader* command with WIC, you should explicitly configure the *.wks.in* file to use the *extlinux.conf* file generated by this class with `--configfile="${DEPLOY_DIR_IMAGE}/extlinux.conf"`. Otherwise it generates a default *extlinux.conf* file without taking this class into account.

**6.6.172 uboot-sign**

The *uboot-sign* class provides support for U-Boot verified boot. It is intended to be inherited from U-Boot recipes.

The variables used by this class are:

- *SPL\_MKIMAGE\_DTCOPTS*: DTC options for U-Boot *mkimage* when building the FIT image.
- *SPL\_SIGN\_ENABLE*: enable signing the FIT image.
- *SPL\_SIGN\_KEYDIR*: directory containing the signing keys.
- *SPL\_SIGN\_KEYNAME*: base filename of the signing keys.
- *SPL\_DTB\_BINARY*: Name of the SPL device tree binary. Can be set to an empty string to indicate that no SPL should be created and added to the FIT image.
- *UBOOT\_FIT\_ADDRESS\_CELLS*: `#address-cells` value for the FIT image.
- *UBOOT\_FIT\_DESC*: description string encoded into the FIT image.
- *UBOOT\_FIT\_GENERATE\_KEYS*: generate the keys if they don't exist yet.
- *UBOOT\_FIT\_HASH\_ALG*: hash algorithm for the FIT image.
- *UBOOT\_FIT\_KEY\_GENRSA\_ARGS*: `openssl genrsa` arguments.
- *UBOOT\_FIT\_KEY\_REQ\_ARGS*: `openssl req` arguments.
- *UBOOT\_FIT\_SIGN\_ALG*: signature algorithm for the FIT image.
- *UBOOT\_FIT\_SIGN\_NUMBITS*: size of the private key for FIT image signing.
- *UBOOT\_FIT\_KEY\_SIGN\_PKCS*: algorithm for the public key certificate for FIT image signing.
- *UBOOT\_FITIMAGE\_ENABLE*: enable the generation of a U-Boot FIT image.
- *UBOOT\_MKIMAGE\_DTCOPTS*: DTC options for U-Boot *mkimage* when rebuilding the FIT image containing the kernel.
- *UBOOT\_FIT\_ARM\_TRUSTED\_FIRMWARE*: include the Trusted Firmware-A (TF-A) binary in the U-Boot FIT image.
- *UBOOT\_FIT\_ARM\_TRUSTED\_FIRMWARE\_IMAGE*: specifies the path to the Trusted Firmware-A (TF-A) binary.
- *UBOOT\_FIT\_TEE*: include the Trusted Execution Environment (TEE) binary in the U-Boot FIT image.
- *UBOOT\_FIT\_TEE\_IMAGE*: specifies the path to the Trusted Execution Environment (TEE) binary.
- *UBOOT\_FIT\_USER\_SETTINGS*: adds a user-specific snippet to the U-Boot Image Tree Source (ITS). Users can include their custom U-Boot Image Tree Source (ITS) snippet in this variable.

- `UBOOT_FIT_CONF_FIRMWARE`: adds one image to the `firmware` property of the configuration node.
- `UBOOT_FIT_CONF_USER_LOADABLES`: adds one or more user-defined images to the `loadables` property of the configuration node.

See U-Boot's documentation for details about [verified boot](#) and the [signature process](#).

See also the description of [kernel-fit-image](#) class, which this class imitates.

### 6.6.173 uki

The `uki` class provides support for [Unified Kernel Image \(UKI\)](#) format. UKIs combine kernel, [Initramfs](#), signatures, metadata etc to a single UEFI firmware compatible binary. The class is intended to be inherited by rootfs image recipes. The build configuration should also use an [Initramfs](#), `systemd-boot` as boot menu provider and have UEFI support on target hardware. Using `systemd` as `init` is recommended. Image builds should create an ESP partition for UEFI firmware and copy `systemd-boot` and UKI files there. Sample configuration for Wic images is provided in `meta/files/wic/efi-uki-bootdisk.wks.in` UKIs are generated using `systemd` reference implementation [ukify](#). This class uses a number of variables but tries to find sensible defaults for them.

The variables used by this class are:

- `EFI_ARCH`: architecture name within EFI standard, set in `meta/conf/image-uefi.conf`
- `IMAGE_EFI_BOOT_FILES`: files to install to EFI boot partition created by the `bootimg_efi` Wic plugin
- `INITRAMFS_IMAGE`: `initramfs` recipe name
- `KERNEL_DEVICETREE`: optional devicetree files to embed into UKI
- `UKIFY_CMD`: `ukify` command to build the UKI image
- `UKI_CMDLINE`: kernel command line to use with UKI
- `UKI_CONFIG_FILE`: optional config file for `ukify`
- `UKI_FILENAME`: output file name for the UKI image
- `UKI_KERNEL_FILENAME`: kernel image file name
- `UKI_SB_CERT`: optional UEFI secureboot certificate matching the private key
- `UKI_SB_KEY`: optional UEFI secureboot private key to sign UKI with
- `UKI_DEVICETREE`: list of device tree blobs to include in the UKI

For examples on how to use this class see oeqa selftest `meta/lib/oeqa/selftest/cases/uki.py`. Also an oeqa runtime test `meta/lib/oeqa/runtime/cases/uki.py` is provided which verifies that the target system booted the same UKI binary as was set at buildtime via `UKI_FILENAME`.

### 6.6.174 uninative

The `uninative` class allows binaries to run on systems with older or newer [Glibc](#) versions. This means [native](#) recipe *Cache di Shared State* can be shared among different host distributions of different versions, i.e. the *Cache di Shared State* is "universal".

To allow this to work, the dynamic loader is changed to our own `ld.so` when binaries are compiled using the `--dynamic-linker` option. This means when the binary is executed, it finds our own `ld.so` and that loader has a modified search path which finds a newer Glibc version.

The linking of the binaries is not changed at link time since the headers on the system wouldn't match the newer Glibc and this causes obtuse failures. Changing the loader is effectively the same as if the system had a Glibc upgrade after the binary was compiled, so it is a mechanism supported by upstream.

One caveat to this approach is that the uninitative Glibc binary must be equal to or newer in version to the versions on all the systems using the common *Cache di Shared State*. This is why *uninitative* is regularly changed on the development and stable branches.

Another potential issue is static linking: static libraries created on a system with a new Glibc version may have symbols not present in older versions, which would then fail during linking on older systems. This is one reason we don't use static linking for our *native* binaries.

With this class enabled, a tarball containing a pre-built C library is downloaded at the start of the build. In *OpenEmbedded-Core (OE-Core)* this is enabled by default through `meta/conf/distro/include/yocto-uninitative.inc`. Other distributions that do not derive from *Poky* can also "require `conf/distro/include/yocto-uninitative.inc`" to use this. Alternatively if you prefer, you can build the uninitative-tarball recipe yourself, publish the resulting tarball (e.g. via HTTP) and set `UNINITATIVE_URL` and `UNINITATIVE_CHECKSUM` appropriately. For an example, see `meta/conf/distro/include/yocto-uninitative.inc`.

The *uninitative* class is also used unconditionally by the *extensible SDK*. When building the extensible SDK, `uninitative-tarball` is built and the resulting tarball is included within the SDK.

### 6.6.175 update-alternatives

The *update-alternatives* class helps the alternatives system when multiple sources provide the same command. This situation occurs when several programs that have the same or similar function are installed with the same name. For example, the `ar` command is available from the `busybox`, `binutils` and `elfutils` packages. The *update-alternatives* class handles renaming the binaries so that multiple packages can be installed without conflicts. The `ar` command still works regardless of which packages are installed or subsequently removed. The class renames the conflicting binary in each package and symlinks the highest priority binary during installation or removal of packages.

To use this class, you need to define a number of variables:

- `ALTERNATIVE`
- `ALTERNATIVE_LINK_NAME`
- `ALTERNATIVE_TARGET`
- `ALTERNATIVE_PRIORITY`

These variables list alternative commands needed by a package, provide pathnames for links, default links for targets, and so forth. For details on how to use this class, see the comments in the `update-alternatives.bbclass` file.

#### Nota

You can use the `update-alternatives` command directly in your recipes. However, this class simplifies things in most cases.



### 6.6.176 `update-rc.d`

The *update-rc.d* class uses `update-rc.d` to safely install an initialization script on behalf of the package. The OpenEmbedded build system takes care of details such as making sure the script is stopped before a package is removed and started when the package is installed.

Three variables control this class: *INITSCRIPT\_PACKAGES*, *INITSCRIPT\_NAME* and *INITSCRIPT\_PARAMS*. See the variable links for details.

### 6.6.177 `upstream-stable-release-point`

The *upstream-stable-release-point* class automatically generates the *UPSTREAM\_STABLE\_RELEASE\_REGEX* variable for recipes whose version uses a dot-separated scheme. This enables stable point release upgrades -- version upgrades constrained to the same stable series (e.g. 1.4.2 to 1.4.3 but not to 1.5.0).

The class uses the *STABLE\_VERSION\_PARTS* variable (defaults to "2") to determine how many leading dot-separated parts of *PV* constitute the stable prefix. For example:

- With *PV* = "1.4.2" and *STABLE\_VERSION\_PARTS* = "2" (default), the generated regex is `^1\.4(\.\d+)*$`.
- With *PV* = "259.5" and *STABLE\_VERSION\_PARTS* = "1" (e.g. `systemd`), the generated regex is `^259(\.\d+)*$`.

For recipes whose stable version part is not dot-separated (e.g. `openssh` uses 10.2p1), set *UPSTREAM\_STABLE\_RELEASE\_REGEX* directly instead of inheriting this class.

### 6.6.178 `useradd*`

The *useradd\** classes support the addition of users or groups for usage by the package on the target. For example, if you have packages that contain system services that should be run under their own user or group, you can use these classes to enable creation of the user or group. The *meta-skeleton/recipes-skeleton/useradd/useradd-example.bb* recipe in *OpenEmbedded-Core (OE-Core)* provides a simple example that shows how to add three users and groups to two packages.

The *useradd\_base* class provides basic functionality for user or groups settings.

The *useradd\** classes support the *USERADD\_PACKAGES*, *USERADD\_PARAM*, *GROUPADD\_PARAM*, and *USERMOD\_PARAM* variables.

The *useradd-staticids* class supports the addition of users or groups that have static user identification (*uid*) and group identification (*gid*) values.

The default behavior of the OpenEmbedded build system for assigning *uid* and *gid* values when packages add users and groups during package install time is to add them dynamically. This works fine for programs that do not care what the values of the resulting users and groups become. In these cases, the order of the installation determines the final *uid* and *gid* values. However, if non-deterministic *uid* and *gid* values are a problem, you can override the default, dynamic application of these values by setting static values. When you set static values, the OpenEmbedded build system looks in *BBPATH* for `files/passwd` and `files/group` files for the values.

To use static `uid` and `gid` values, you need to set some variables. See the [USERADDEXTENSION](#), [USERADD\\_UID\\_TABLES](#), [USERADD\\_GID\\_TABLES](#), and [USERADD\\_ERROR\\_DYNAMIC](#) variables. You can also see the `useradd*` class for additional information.

**i Nota**

You do not use the `useradd-staticids` class directly. You either enable or disable the class by setting the [USERADDEXTENSION](#) variable. If you enable or disable the class in a configured system, [TMPDIR](#) might contain incorrect `uid` and `gid` values. Deleting the [TMPDIR](#) directory will correct this condition.

### 6.6.179 `utility-tasks`

The `utility-tasks` class provides support for various "utility" type tasks that are applicable to all recipes, such as `do_clean` and `do_listtasks`.

This class is enabled by default because it is inherited by the `base` class.

### 6.6.180 `utils`

The `utils` class provides some useful Python functions that are typically used in inline Python expressions (e.g. `${@. . .}`). One example use is for `bb.utils.contains()`.

This class is enabled by default because it is inherited by the `base` class.

### 6.6.181 `vala`

The `vala` class supports recipes that need to build software written using the Vala programming language.

### 6.6.182 `vex`

The `vex` class is used to generate metadata needed by external tools to check for vulnerabilities, for example CVEs.

In order to use this class, inherit the class in your `build/conf/local.conf` or distro `configuration file` and it will add the `generate_vex` task for every recipe:

```
INHERIT += "vex"
```

If an image is built it will generate a report in [DEPLOY\\_DIR\\_IMAGE](#) for all the packages used, it will also generate a file for all recipes used in the build.

Example usage:

```
bitbake -c generate_vex openssl
```

### 6.6.183 `waf`

The `waf` class supports recipes that need to build software that uses the Waf build system. You can use the [EXTRA\\_OECONF](#) or [PACKAGECONFIG\\_CONFARGS](#) variables to specify additional configuration options to be passed on the Waf command line.

### 6.6.184 yocto-check-layer

The *yocto-check-layer* class is used by the *yocto-check-layer* script to ensure that packages from Yocto Project Compatible layers don't skip required QA checks listed in *CHECKLAYER\_REQUIRED\_TESTS* defined by the *insane* class.

It adds an anonymous python function with extra processing to all recipes, and globally inheriting this class with *INHERIT* is not advised. Instead the *yocto-check-layer* script should be used as it handles usage of this class.

For more information on the Yocto Project Compatible layers, see the *Making Sure Your Layer is Compatible With Yocto Project* section of the Yocto Project Development Manual.

## 6.7 | Task

Tasks are units of execution for BitBake. Recipes (.bb files) use tasks to complete configuring, compiling, and packaging software. This chapter provides a reference of the tasks defined in the OpenEmbedded build system.

To see the tasks defined (in alphabetical order) for a given recipe, you can run:

```
$ bitbake -c listtasks recipename
do_build                Default task for a recipe - depends on all_
↳ other normal tasks required to 'build' a recipe
do_checkuri             Validates the SRC_URI value
do_clean                Removes all output files for a target_
↳ including ${WORKDIR}, sstate manifests and stamps
do_cleanall             Removes all output files, shared state cache,
↳ and downloaded source files for a target
do_cleansstate          Removes all output files and shared state_
↳ cache for a target
do_compile              Compiles the source in the compilation_
↳ directory
...
```

In addition, once a recipe has been built, you can examine the resulting task information in that recipe's `${WORKDIR}/temp/` directory, which will consist of the following:

- for each task, a `run` file that represents the code that was executed for that task
- for each task, a corresponding `log` file showing the result of task execution
- a single `log.task_order` file showing the execution order of all tasks for that recipe

### 6.7.1 Normal Recipe Build Tasks

The following sections describe normal tasks associated with building a recipe. For more information on tasks and dependencies, see the "Tasks" and "Dependencies" sections in the BitBake User Manual.

### `do_build`

The default task for all recipes. This task depends on all other normal tasks required to build a recipe.

### `do_compile`

Compiles the source code. This task runs with the current working directory set to `${B}`.

The default behavior of this task is to run the `oe_runmake` function if a makefile (Makefile, makefile, or GNUmakefile) is found. If no such file is found, the `do_compile` task does nothing.

### `do_compile_ptest_base`

Compiles the runtime test suite included in the software being built.

### `do_configure`

Configures the source by enabling and disabling any build-time and configuration options for the software being built. The task runs with the current working directory set to `${B}`.

The default behavior of this task is to run `oe_runmake clean` if a makefile (Makefile, makefile, or GNUmakefile) is found and `CLEANBROKEN` is not set to "1". If no such file is found or the `CLEANBROKEN` variable is set to "1", the `do_configure` task does nothing.

### `do_configure_ptest_base`

Configures the runtime test suite included in the software being built.

### `do_deploy`

Writes output files that are to be deployed to `${DEPLOY_DIR_IMAGE}`. The task runs with the current working directory set to `${B}`.

Recipes implementing this task should inherit the `deploy` class and should write the output to `${DEPLOYDIR}`, which is not to be confused with `${DEPLOY_DIR}`. The `deploy` class sets up `do_deploy` as a shared state (sstate) task that can be accelerated through sstate use. The sstate mechanism takes care of copying the output from `${DEPLOYDIR}` to `${DEPLOY_DIR_IMAGE}`.

#### Nota

Do not write the output directly to `${DEPLOY_DIR_IMAGE}`, as this causes the sstate mechanism to malfunction.

The `do_deploy` task is not added as a task by default and consequently needs to be added manually. If you want the task to run after `do_compile`, you can add it by doing the following:

```
addtask deploy after do_compile
```

Adding `do_deploy` after other tasks works the same way.

**i Nota**

You do not need to add `before do_build` to the `addtask` command (though it is harmless), because the *base* class contains the following:

```
do_build[recrdeptask] += "do_deploy"
```

See the "[Dependencies](#)" section in the BitBake User Manual for more information.

If the *do\_deploy* task re-executes, any previous output is removed (i.e. "cleaned").

**do\_fetch**

Fetches the source code. This task uses the *SRC\_URI* variable and the argument's prefix to determine the correct *fetcher* module.

**do\_image**

Starts the image generation process. The *do\_image* task runs after the OpenEmbedded build system has run the *do\_rootfs* task during which packages are identified for installation into the image and the root filesystem is created, complete with post-processing.

The *do\_image* task performs pre-processing on the image through the *IMAGE\_PREPROCESS\_COMMAND* and dynamically generates supporting *do\_image\_\** tasks as needed.

For more information on image creation, see the "[Generazione dell'Immagine](#)" section in the Yocto Project Overview and Concepts Manual.

**do\_image\_complete**

Completes the image generation process. The *do\_image\_complete* task runs after the OpenEmbedded build system has run the *do\_image* task during which image pre-processing occurs and through dynamically generated *do\_image\_\** tasks the image is constructed.

The *do\_image\_complete* task performs post-processing on the image through the *IMAGE\_POSTPROCESS\_COMMAND*.

For more information on image creation, see the "[Generazione dell'Immagine](#)" section in the Yocto Project Overview and Concepts Manual.

**do\_install**

Copies files that are to be packaged into the holding area  $\${D}$ . This task runs with the current working directory set to  $\${B}$ , which is the compilation directory. The *do\_install* task, as well as other tasks that either directly or indirectly depend on the installed files (e.g. *do\_package*, *do\_package\_write\_\**, and *do\_rootfs*), run under *fakeroot*.

**i Nota**

When installing files, be careful not to set the owner and group IDs of the installed files to unintended values. Some methods of copying files, notably when using the recursive `cp` command, can preserve the UID and/or GID

of the original file, which is usually not what you want. The `host-user-contaminated` QA check checks for files that probably have the wrong ownership.

Safe methods for installing files include the following:

- The `install` utility. This utility is the preferred method.
- The `cp` command with the `--no-preserve=ownership` option.
- The `tar` command with the `--no-same-owner` option. See the `bin_package.bbclass` file in the `meta/classes-recipe` subdirectory of *OpenEmbedded-Core (OE-Core)* for an example.

### `do_install_ptest_base`

Copies the runtime test suite files from the compilation directory to a holding area.

### `do_package`

Analyzes the content of the holding area `${D}` and splits the content into subsets based on available packages and files. This task makes use of the `PACKAGES` and `FILES` variables.

The `do_package` task, in conjunction with the `do_packagedata` task, also saves some important package metadata. For additional information, see the `PKGDESTWORK` variable and the "*Dipendenze di Runtime Aggiunte Automaticamente*" section in the Yocto Project Overview and Concepts Manual.

### `do_package_qa`

Runs QA checks on packaged files. For more information on these checks, see the *QA Error and Warning Messages* document.

### `do_package_write_deb`

Creates Debian packages (i.e. `*.deb` files) and places them in the `${DEPLOY_DIR_DEB}` directory in the package feeds area. For more information, see the "*Feed dei Pacchetti*" section in the Yocto Project Overview and Concepts Manual.

### `do_package_write_ipk`

Creates IPK packages (i.e. `*.ipk` files) and places them in the `${DEPLOY_DIR_IPK}` directory in the package feeds area. For more information, see the "*Feed dei Pacchetti*" section in the Yocto Project Overview and Concepts Manual.

### `do_package_write_rpm`

Creates RPM packages (i.e. `*.rpm` files) and places them in the `${DEPLOY_DIR_RPM}` directory in the package feeds area. For more information, see the "*Feed dei Pacchetti*" section in the Yocto Project Overview and Concepts Manual.

## do\_packagedata

Saves package metadata generated by the *do\_package* task in *PKGDATA\_DIR* to make it available globally.

## do\_patch

Locates patch files and applies them to the source code.

After fetching and unpacking source files, the build system uses the recipe's *SRC\_URI* statements to locate and apply patch files to the source code.

### Nota

The build system uses the *FILESPATH* variable to determine the default set of directories when searching for patches.

Patch files, by default, are \*.patch and \*.diff files created and kept in a subdirectory of the directory holding the recipe file. For example, consider the *bluez5* recipe from the *OpenEmbedded-Core (OE-Core)* layer:

```
meta/recipes-connectivity/bluez5
```

This recipe has two patch files located here:

```
meta/recipes-connectivity/bluez5/bluez5
```

In the *bluez5* recipe, the *SRC\_URI* statements point to the source and patch files needed to build the package.

### Nota

In the case for the *bluez5\_5.48.bb* recipe, the *SRC\_URI* statements are from an include file *bluez5.inc*.

As mentioned earlier, the build system treats files whose file types are .patch and .diff as patch files. However, you can use the "apply=yes" parameter with the *SRC\_URI* statement to indicate any file as a patch file:

```
SRC_URI = " \
    git://path_to_repo/some_package \
    file://file;apply=yes \
"
```

Conversely, if you have a file whose file type is .patch or .diff and you want to exclude it so that the *do\_patch* task does not apply it during the patch phase, you can use the "apply=no" parameter with the *SRC\_URI* statement:

```
SRC_URI = " \
    git://path_to_repo/some_package \
    file://file1.patch \
    file://file2.patch;apply=no \
"
```

In the previous example `file1.patch` would be applied as a patch by default while `file2.patch` would not be applied.

You can find out more about the patching process in the "*Applicazione delle Patch*" section in the Yocto Project Overview and Concepts Manual and the "*Patching Code*" section in the Yocto Project Development Tasks Manual.

### `do_populate_lic`

Writes license information for the recipe that is collected later when the image is constructed.

### `do_populate_sdk`

Creates the file and directory structure for an installable SDK. See the "*Generazione dell'SDK*" section in the Yocto Project Overview and Concepts Manual for more information.

### `do_populate_sdk_ext`

Creates the file and directory structure for an installable extensible SDK (eSDK). See the "*Generazione dell'SDK*" section in the Yocto Project Overview and Concepts Manual for more information.

### `do_populate_sysroot`

Stages (copies) a subset of the files installed by the `do_install` task into the appropriate sysroot. For information on how to access these files from other recipes, see the `STAGING_DIR*` variables. Directories that would typically not be needed by other recipes at build time (e.g. `/etc`) are not copied by default.

For information on what directories are copied by default, see the `SYSROOT_DIRS*` variables. You can change these variables inside your recipe if you need to make additional (or fewer) directories available to other recipes at build time.

The `do_populate_sysroot` task is a shared state (sstate) task, which means that the task can be accelerated through sstate use. Realize also that if the task is re-executed, any previous output is removed (i.e. "cleaned").

### `do_prepare_recipe_sysroot`

Installs the files into the individual recipe specific sysroots (i.e. `recipe-sysroot` and `recipe-sysroot-native` under `$(WORKDIR)` based upon the dependencies specified by `DEPENDS`). See the "*staging*" class for more information.

### `do_recipe_qa`

Performs QA check on recipes that can operate entirely from recipe metadata and do not need any of the build artefacts or source code.

The list of QA checks that this tasks defines are documented in *QA Error and Warning Messages*.

### `do_rm_work`

Removes work files after the OpenEmbedded build system has finished with them. You can learn more by looking at the "*rm\_work*" section.



### do\_unpack

Unpacks the source code into a working directory pointed to by `${UNPACKDIR}`. For more information on how source files are unpacked, see the "*Prelievo del Codice Sorgente*" section in the Yocto Project Overview and Concepts Manual.

## 6.7.2 Manually Called Tasks

These tasks are typically manually triggered (e.g. by using the `bitbake -c` command-line option) because they are not normally part of any standard build workflow. As an example, consider the `listtasks` task, which displays the tasks defined for a given recipe and would be invoked with:

```
$ bitbake -c listtasks recipename
```

A typical definition of a manually-called task would look like:

```
addtask listtasks
do_listtasks[nostamp] = "1"
python do_listtasks() {
    ... definition of task ...
}
```

which defines that function as a task without building it into any task dependency chain, as well as setting the `[nostamp]` flag to ensure that it is run every time it is invoked.

### do\_checkuri

Validates the `SRC_URI` value.

### do\_clean

Removes all output files for a target from the `do_unpack` task forward (i.e. `do_unpack`, `do_configure`, `do_compile`, `do_install`, and `do_package`).

You can run this task using BitBake as follows:

```
$ bitbake -c clean recipe
```

Running this task removes the working directory of the recipe (represented by its `WORKDIR` value), the sstate manifests and the `stamps`. However, it does not remove the `sstate` cache files. Consequently, if no changes have been made and the recipe is rebuilt after cleaning, output files are simply restored from the sstate cache. If you want to remove the sstate cache files for the recipe, you need to use the `do_cleansstate` task instead (i.e. `bitbake -c cleansstate recipe`).

### `do_cleanall`

Removes all output files, shared state (*sstate*) cache, and downloaded source files for a target (i.e. the contents of *DL\_DIR*). Essentially, the *do\_cleanall* task is identical to the *do\_cleansstate* task with the added removal of downloaded source files.

You can run this task using BitBake as follows:

```
$ bitbake -c cleanall recipe
```

You should never use the *do\_cleanall* task in a normal scenario. If you want to start fresh with the *do\_fetch* task, use instead:

```
$ bitbake -f -c fetch recipe
```

#### Nota

The reason to prefer `bitbake -f -c fetch` is that the *do\_cleanall* task would break in some cases, such as:

```
$ bitbake -c fetch      recipe
$ bitbake -c cleanall  recipe-native
$ bitbake -c unpack    recipe
```

because after step 1 there is a stamp file for the *do\_fetch* task of `recipe`, and it won't be removed at step 2 because step 2 uses a different work directory. So the unpack task at step 3 will try to extract the downloaded archive and fail as it has been deleted in step 2.

Note that this also applies to BitBake from concurrent processes when a shared download directory (*DL\_DIR*) is setup.

### `do_cleansstate`

Removes all output files and shared state (*sstate*) cache for a target. Essentially, the *do\_cleansstate* task is identical to the *do\_clean* task with the added removal of shared state (*sstate*) cache.

You can run this task using BitBake as follows:

```
$ bitbake -c cleansstate recipe
```

When you run the *do\_cleansstate* task, the OpenEmbedded build system no longer uses any *sstate*. Consequently, building the recipe from scratch is guaranteed.

#### Nota

Using *do\_cleansstate* with a shared *SSTATE\_DIR* is not recommended because it could trigger an error during the build of a separate BitBake instance. This is because the builds check *sstate* "up front" but download the files later, so if it is deleted in the meantime, it will cause an error but not a total failure as it will rebuild it.

The reliable and preferred way to force a new build is to use `bitbake -f` instead.

**i Nota**

The *do\_cleansstate* task cannot remove sstate from a remote sstate mirror. If you need to build a target from scratch using remote mirrors, use the "-f" option as follows:

```
$ bitbake -f -c do_cleansstate target
```

**do\_pydevshell**

Starts a shell in which an interactive Python interpreter allows you to interact with the BitBake build environment. From within this shell, you can directly examine and set bits from the data store and execute functions as if within the BitBake environment. See the "*Using a Python Development Shell*" section in the Yocto Project Development Tasks Manual for more information about using *pydevshell*.

**do\_devshell**

Starts a shell whose environment is set up for development, debugging, or both. See the "*Using a Development Shell*" section in the Yocto Project Development Tasks Manual for more information about using *devshell*.

**do\_list\_image\_features**

Lists the available features for an image recipe. These features can be set through either the *IMAGE\_FEATURES* or *EXTRA\_IMAGE\_FEATURES* variables.

**do\_listtasks**

Lists all defined tasks for a target.

**do\_package\_index**

Creates or updates the index in the *Feed dei Pacchetti* area.

**i Nota**

This task is not triggered with the `bitbake -c` command-line option as are the other tasks in this section. Because this task is specifically for the `package-index` recipe, you run it using `bitbake package-index`.

### 6.7.3 Image-Related Tasks

The following tasks are applicable to image recipes.

**do\_bootimg**

Creates a bootable live image. See the *IMAGE\_FSTYPES* variable for additional information on live image types.

#### `do_bundle_initramfs`

Combines an *initramfs* image and kernel together to form a single image.

#### `do_rootfs`

Creates the root filesystem (file and directory structure) for an image. See the "*Generazione dell'Immagine*" section in the Yocto Project Overview and Concepts Manual for more information on how the root filesystem is created.

#### `do_testimage`

Boots an image and performs runtime tests within the image. For information on automatically testing images, see the "*Performing Automated Runtime Testing*" section in the Yocto Project Test Environment Manual.

#### `do_testimage_auto`

Boots an image and performs runtime tests within the image immediately after it has been built. This task is enabled when you set *TESTIMAGE\_AUTO* equal to "1".

For information on automatically testing images, see the "*Performing Automated Runtime Testing*" section in the Yocto Project Test Environment Manual.

### 6.7.4 Kernel-Related Tasks

The following tasks are applicable to kernel recipes. Some of these tasks (e.g. the *do\_menuconfig* task) are also applicable to recipes that use Linux kernel style configuration such as the BusyBox recipe.

#### `do_compile_kernelmodules`

Runs the step that builds the kernel modules (if needed). Building a kernel consists of two steps: 1) the kernel (*vmlinux*) is built, and 2) the modules are built (i.e. `make modules`).

#### `do_diffconfig`

When invoked by the user, this task creates a file containing the differences between the original config as produced by *do\_kernel\_configme* task and the changes made by the user with other methods (i.e. using (*do\_menuconfig*)). Once the file of differences is created, it can be used to create a config fragment that only contains the differences. You can invoke this task from the command line as follows:

```
$ bitbake linux-yocto -c diffconfig
```

For more information, see the "*Creating Configuration Fragments*" section in the Yocto Project Linux Kernel Development Manual.

#### `do_kernel_checkout`

Converts the newly unpacked kernel source into a form with which the OpenEmbedded build system can work. Because the kernel source can be fetched in several different ways, the *do\_kernel\_checkout* task makes sure that subsequent tasks are given a clean working tree copy of the kernel with the correct branches checked out.

### `do_kernel_configcheck`

Validates the configuration produced by the `do_menuconfig` task. The `do_kernel_configcheck` task produces warnings when a requested configuration does not appear in the final `.config` file or when you override a policy configuration in a hardware configuration fragment. You can run this task explicitly and view the output by using the following command:

```
$ bitbake linux-yocto -c kernel_configcheck -f
```

For more information, see the "*Validating Configuration*" section in the Yocto Project Linux Kernel Development Manual.

### `do_kernel_configme`

After the kernel is patched by the `do_patch` task, the `do_kernel_configme` task assembles and merges all the kernel config fragments into a merged configuration that can then be passed to the kernel configuration phase proper. This is also the time during which user-specified defconfigs are applied if present, and where configuration modes such as `--allnoconfig` are applied.

### `do_kernel_metadata`

Collects all the features required for a given kernel build, whether the features come from `SRC_URI` or from Git repositories. After collection, the `do_kernel_metadata` task processes the features into a series of config fragments and patches, which can then be applied by subsequent tasks such as `do_patch` and `do_kernel_configme`.

### `do_menuconfig`

Invoked by the user to manipulate the `.config` file used to build a linux-yocto recipe. This task starts the Linux kernel configuration tool, which you then use to modify the kernel configuration.

You can invoke this tool from the command line as follows:

```
$ bitbake linux-yocto -c menuconfig
```

See the "*Using menuconfig*" section in the Yocto Project Linux Kernel Development Manual for more information on this configuration tool.

### `do_savedefconfig`

When invoked by the user, creates a defconfig file that can be used instead of the default defconfig. The saved defconfig contains the differences between the default defconfig and the changes made by the user using other methods (i.e. the `do_menuconfig` task). You can invoke the task using the following command:

```
$ bitbake linux-yocto -c savedefconfig
```

### `do_shared_workdir`

After the kernel has been compiled but before the kernel modules have been compiled, this task copies files required for module builds and which are generated from the kernel build into the shared work directory. With these copies successfully copied, the `do_compile_kernelmodules` task can successfully build the kernel modules in the next step of the build.

### `do_sizecheck`

If the variable `KERNEL_IMAGE_MAXSIZE` is set, this task compares the size of all stripped kernel images listed in `KERNEL_IMAGETYPES` against that value. If more than one image type is listed there, warn on any that exceed that value, but fail only if none of them fit.

### `do_strip`

If `KERNEL_IMAGE_STRIP_EXTRA_SECTIONS` is defined, this task strips the sections named in that variable from `vmlinux`. This stripping is typically used to remove nonessential sections such as `.comment` sections from a size-sensitive configuration.

Common sections to strip:

- `.comment`: Holds compiler version strings and information
- `.note.*`: Extra notes often left by the compiler
- `.debug`: Debugging information

### `do_validate_branches`

After the kernel is unpacked but before it is patched, this task makes sure that the machine and metadata branches as specified by the `SRCREV` variables actually exist on the specified branches. Otherwise, if `AUTOREV` is not being used, the `do_validate_branches` task fails during the build.

## 6.8 Using Configuration Fragments

*Configuration Fragments* define top level build configuration features that can be independently enabled and disabled using standard tooling. Such features are made of one or several build configuration statements that are either contained in a fragment file, or are set indirectly using the *Built-in Fragment* mechanism.

This document provides a quick reference of the `bitbake-config-build` tool and lists the *Configuration Fragments* and *Built-in Fragments* available in the *OpenEmbedded Build System* core repositories.

**i Nota**

For details on how to define new fragments in your build, see the *Creating New Configuration Fragments In Your Build* section of the Yocto Project Development Tasks Manual.

### 6.8.1 bitbake-config-build Quick Reference

*Configuration Fragments* are managed with the `bitbake-config-build` command-line tool, which is available after *Initializing the Build Environment*.

The `bitbake-config-build` command-line tool uses sub-commands to manage fragments, which are detailed in the sections below. For each sub-command, the `--help` flag can be passed to get more information on the sub-command.

#### `bitbake-config-build list-fragments`

The `bitbake-config-build list-fragments` command will list the *Built-in Fragments* and *Configuration Fragments* that are currently available, and will also print which fragments are enabled or disabled.

#### `bitbake-config-build show-fragment`

The `bitbake-config-build show-fragment` command is used to show the location and value of a fragment. For example, running `bitbake-config-build show-fragment core/yocto/sstate-mirror-cdn` will show the content of the `core/yocto/sstate-mirror-cdn` fragment.

#### `bitbake-config-build enable-fragment`

The `bitbake-config-build enable-fragment` command is used to enable a fragment. When a fragment is enabled, the configuration variables of this fragment are parsed by *BitBake* and their values are available globally in your build.

From the list obtained with the `bitbake-config-build list-fragments` command, you can determine which fragments can be enabled for your build.

For example, the following command would enable the `core/yocto/sstate-mirror-cdn` fragment:

```
bitbake-config-build enable-fragment core/yocto/sstate-mirror-cdn
```

**i Nota**

Multiple fragments can be enabled at once with the same command:

```
bitbake-config-build enable-fragment <fragment1> <fragment2> ...
```

*Built-in fragments* are enabled the same way, and their values are defined from the command-line directly. For example, the following command sets the `qemuarm64` *MACHINE* through the `machine/` fragment:

```
bitbake-config-build enable-fragment machine/qemuarm64
```

This fragment can be overridden from the command-line by setting it to another value, for example:

```
bitbake-config-build enable-fragment machine/qemux86-64
```

In the above example, the new value of *MACHINE* is now equal to `qemux86-64`.

When a fragment is enabled with *bitbake-config-build enable-fragment*, its name is automatically appended to the *OE\_FRAGMENTS* variable in *build/conf/toolcfg.conf*.

#### Nota

It is also possible to manually remove or add fragments by modifying the *OE\_FRAGMENTS* variable in a configuration file such as *build/conf/local.conf*.

### **bitbake-config-build disable-fragment**

Any fragment enabled with the *bitbake-config-build enable-fragment* command can be disabled with the *bitbake-config-build disable-fragment* command. The list of enabled fragments can be obtained with *bitbake-config-build list-fragments*.

For example, the following command disables the *core/yocto/sstate-mirror-cdn* fragment:

```
bitbake-config-build disable-fragment core/yocto/sstate-mirror-cdn
```

Likewise, *Built-in Fragments* are disabled the same way. For example, this would disable the *machine/qemuarm64* fragment:

```
bitbake-config-build disable-fragment machine/qemuarm64
```

#### Nota

Multiple fragments can be disabled at once with the same command:

```
bitbake-config-build disable-fragment <fragment1> <fragment2>
```

### **bitbake-config-build disable-all-fragments**

The *bitbake-config-build disable-all-fragments* command disables all of the currently enabled fragments. The list of enabled fragments can be obtained with *bitbake-config-build list-fragments*.

This command is run without arguments:

```
bitbake-config-build disable-all-fragments
```

## 6.8.2 Core Fragments

### Core Built-in Fragments

*Built-in Fragments* are used to assign a single variable globally. The *OpenEmbedded Build System* defines multiple built-in fragments that are detailed in this section.



### `machine/`

The `machine/` *built-in fragment* can be used to assign the value of the `MACHINE` variable globally.

### `distro/`

The `distro/` *built-in fragment* can be used to assign the value of the `DISTRO` variable globally.

## Core Configuration Fragments

### Yocto Project Fragments

This group defines fragments related to the Yocto Project infrastructure in general.

#### `core/yocto/sstate-mirror-cdn`

The `core/yocto/sstate-mirror-cdn` *configuration fragment* can be used to set up `BB_HASHSERVE_UPSTREAM` and `SSTATE_MIRRORS` to use pre-built *shared state cache* artifacts for standard Yocto build configurations.

This will mean the build will query the Yocto Project mirrors to check for artifacts at the start of builds, which does slow it down initially but it will then speed up the builds by not having to build things if they are present in the cache. It assumes you can download something faster than you can build it which will depend on your network configuration.

#### `core/yocto/root-login-with-empty-password`

The `core/yocto/root-login-with-empty-password` *configuration fragment* can be used to allow to login as the `root` user to login without a password on the serial console and over SSH.

#### `core/yocto/sbom-cve-check`

The `core/yocto/sbom-cve-check` *configuration fragment* can be used to set up the build to use the *sbom-cve-check* class.

This configuration fragment does multiple things:

- Adds the *create-spdx* class to the list of globally inherited classes, as it depends on it.
- Sets the source revision (*SRCREV*) of the input CVE databases to *AUTOREV*, so these databases are automatically fetched and updated when starting a build.
- Includes the VEX statements to the input SPDX document using the *SPDX\_INCLUDE\_VEX* variable.

#### `core/yocto/monitor-disk-space`

The `core/yocto/monitor-disk-space` *configuration fragment* can be used to produce warnings or errors when the disk currently in use during the build is out of space, by setting a sensible value for the `BB_DISKMON_DIRS` variable. See the definition of `BB_DISKMON_DIRS` for more information.

## Yocto Project Autobuilder Fragments

This group defines fragment used for the Yocto Project Autobuilder. For details, see the *Yocto Project Autobuilder Overview* section of the Yocto Project Test Environment Manual.

### `core/yocto-autobuilder/autobuilder`

The `core/yocto-autobuilder/autobuilder` fragment defines common variables used in builds started by the Yocto Project Autobuilder.

### `core/yocto-autobuilder/autobuilder-resource-constraints`

The `core/yocto-autobuilder/autobuilder` fragment defines variables for limiting the resources used by the Yocto Project Autobuilder during builds. For more details on how to limit resources, see the *Limiting the Host Resources Usage* section of the Yocto Project Development Tasks Manual.

### `core/yocto-autobuilder/multilib-mips64-n32`

The `core/yocto-autobuilder/multilib-mips64-n32` fragment enables tri-architecture *multilib* configurations for MIPS64 machines, which includes `mips64-n32`, `mips64`, and `mips32r2`.

### `core/yocto-autobuilder/multilib-x86-lib32`

The `core/yocto-autobuilder/multilib-x86-lib32` fragment enables *multilib* configurations for supporting 32-bit libraries on 64-bit X86 builds.

### `core/yocto-autobuilder/multilib-x86-lib64`

The `core/yocto-autobuilder/multilib-x86-lib64` fragment enables *multilib* configurations for supporting 64-bit libraries on 32-bit X86 builds.

## 6.9 devtool Quick Reference

The `devtool` command-line tool provides a number of features that help you build, test, and package software. This command is available alongside the `bitbake` command. Additionally, the `devtool` command is a key part of the extensible SDK.

This chapter provides a Quick Reference for the `devtool` command. For more information on how to apply the command when using the extensible SDK, see the "*Using the Extensible SDK*" chapter in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### 6.9.1 Getting Help

The `devtool` command line is organized similarly to Git in that it has a number of sub-commands for each function. You can run `devtool --help` to see all the commands:

```
$ devtool --help
NOTE: Starting bitbake server...
```

(continues on next page)

(continua dalla pagina precedente)

```
usage: devtool [--basepath BASEPATH] [--bbpath BBPATH] [-d] [-q] [--color COLOR]
↳ [-h] <subcommand> ...
```

OpenEmbedded development tool

options:

```
--basepath BASEPATH  Base directory of SDK / build directory
--bbpath BBPATH       Explicitly specify the BBPATH, rather than getting it from
↳ the metadata
-d, --debug           Enable debug output
-q, --quiet           Print only errors
--color COLOR         Colorize output (where COLOR is auto, always, never)
-h, --help            show this help message and exit
```

subcommands:

Beginning work on a recipe:

```
add                  Add a new recipe
modify               Modify the source for an existing recipe
upgrade              Upgrade an existing recipe
```

Getting information:

```
status               Show workspace status
latest-version        Report the latest version of an existing recipe
check-upgrade-status Report upgradability for multiple (or all) recipes
search                Search available recipes
```

Working on a recipe in the workspace:

```
build                Build a recipe
ide-sdk               Setup the SDK and configure the IDE
rename                Rename a recipe file in the workspace
edit-recipe           Edit a recipe file
find-recipe           Find a recipe file
configure-help         Get help on configure script options
update-recipe          Apply changes from external source tree to recipe
reset                 Remove a recipe from your workspace
finish                Finish working on a recipe in your workspace
```

Testing changes on target:

```
deploy-target         Deploy recipe output files to live target machine
undeploy-target        Undeploy recipe output files in live target machine
build-image            Build image including workspace recipe packages
```

Advanced:

```
create-workspace      Set up workspace in an alternative location
import                 Import exported tar archive into workspace
export                 Export workspace into a tar archive
extract                Extract the source for an existing recipe
```

(continues on next page)

(continua dalla pagina precedente)

```

    sync                Synchronize the source tree for an existing recipe
    menuconfig          Alter build-time configuration for a recipe
Use devtool <subcommand> --help to get help on a specific command

```

As directed in the general help output, you can get more syntax on a specific command by providing the command name and using `--help`:

```

$ devtool add --help
NOTE: Starting bitbake server...
usage: devtool add [-h] [--same-dir | --no-same-dir] [--fetch URI] [--npm-dev] [--no-pypi]
    [--version VERSION] [--no-git] [--srcrev SRCREV | --autorev]
    [--srcbranch SRCBRANCH] [--binary] [--also-native] [--src-subdir SUBDIR]
    [--mirrors] [--provides PROVIDES]
    [recipeName] [srcTree] [fetchURI]

Adds a new recipe to the workspace to build a specified source tree. Can
    optionally fetch a remote URI and unpack it to create the source tree.

arguments:
    recipeName          Name for new recipe to add (just name - no version, path
    or extension). If not specified, will attempt to auto-detect it.
    srcTree             Path to external source tree. If not specified, a
    subdirectory of /media/build1/poky/build/workspace/sources will be used.
    fetchURI           Fetch the specified URI and extract it to create the
    source tree

options:
    -h, --help          show this help message and exit
    --same-dir, -s      Build in same directory as source
    --no-same-dir       Force build in a separate build directory
    --fetch URI, -f URI  Fetch the specified URI and extract it to create the
    source tree (deprecated - pass as positional argument instead)
    --npm-dev           For npm, also fetch devDependencies
    --no-pypi           Do not inherit pypi class
    --version VERSION, -V VERSION
                        Version to use within recipe (PV)
    --no-git, -g       If fetching source, do not set up source tree as a git
    repository
    --srcrev SRCREV, -S SRCREV
                        Source revision to fetch if fetching from an SCM such as
    git (default latest)
    --autorev, -a      When fetching from a git repository, set SRCREV in the
    recipe to a floating revision instead of fixed

```

(continues on next page)

(continua dalla pagina precedente)

```


--srcbranch SRCBRANCH, -B SRCBRANCH
                        Branch in source repository if fetching from an SCM such
↳as git (default master)
--binary, -b           Treat the source tree as something that should be
↳installed verbatim (no compilation, same directory structure). Useful with
↳binary packages e.g. RPMs.
--also-native          Also add native variant (i.e. support building recipe for
↳the build host as well as the target machine)
--src-subdir SUBDIR    Specify subdirectory within source tree to use
--mirrors              Enable PREMIRRORS and MIRRORS for source tree fetching
↳(disable by default).
--provides PROVIDES, -p PROVIDES
                        Specify an alias for the item provided by the recipe. E.g.
↳virtual/libgl

```

## 6.9.2 The Workspace Layer Structure

`devtool` uses a "Workspace" layer in which to accomplish builds. This layer is not specific to any single `devtool` command but is rather a common working area used across the tool.

The following figure shows the workspace structure:



**attic** - A directory created if devtool believes it must preserve anything when you run "devtool reset". For example, if you run "devtool add", make changes to the recipe, and then run "devtool reset", devtool takes notice that the file has been changed and moves it into the attic should you still want the recipe.

**README** - Provides information on what is in workspace layer and how to manage it.

**.devtool\_md5** - A checksum file used by devtool.

(continues on next page)

(continua dalla pagina precedente)

```

appends - A directory that contains *.bbappend files, which point to
         external source.

conf - A configuration directory that contains the layer.conf file.

recipes - A directory containing recipes. This directory contains a
         folder for each directory added whose name matches that of the
         added recipe. devtool places the recipe.bb file
         within that sub-directory.

sources - A directory containing a working copy of the source files used
         when building the recipe. This is the default directory used
         as the location of the source tree when you do not provide a
         source tree path. This directory contains a folder for each
         set of source files matched to a corresponding recipe.

```

### 6.9.3 Adding a New Recipe to the Workspace Layer

Use the `devtool add` command to add a new recipe to the workspace layer. The recipe you add should not exist --- `devtool` creates it for you. The source files the recipe uses should exist in an external area.

The following example creates and adds a new recipe named `jackson` to a workspace layer the tool creates. The source code built by the recipes resides in `/home/user/sources/jackson`:

```
$ devtool add jackson /home/user/sources/jackson
```

If you add a recipe and the workspace layer does not exist, the command creates the layer and populates it as described in "[The Workspace Layer Structure](#)" section.

Running `devtool add` when the workspace layer exists causes the tool to add the recipe, append files, and source files into the existing workspace layer. The `.bbappend` file is created to point to the external source tree.

#### Nota

If your recipe has runtime dependencies defined, you must be sure that these packages exist on the target hardware before attempting to run your application. If dependent packages (e.g. libraries) do not exist on the target, your application, when run, will fail to find those functions. For more information, see the "[Deploying Your Software on the Target Machine](#)" section.

By default, `devtool add` uses the latest revision (i.e. master) when unpacking files from a remote URI. In some cases, you might want to specify a source revision by branch, tag, or commit hash. You can specify these options when using the `devtool add` command:

- To specify a source branch, use the `--srcbranch` option:

```
$ devtool add --srcbranch blacksail jackson /home/user/sources/jackson
```

In the previous example, you are checking out the blacksail branch.

- To specify a specific tag or commit hash, use the `--srcrev` option:

```
$ devtool add --srcrev yocto-$DISTRO; jackson /home/user/sources/jackson
$ devtool add --srcrev some_commit_hash /home/user/sources/jackson
```

The previous examples check out the `yocto-$DISTRO;` tag and the commit associated with the `some_commit_hash` hash.

#### Nota

If you prefer to use the latest revision every time the recipe is built, use the options `--autorev` or `-a`.

## 6.9.4 Extracting the Source for an Existing Recipe

Use the `devtool extract` command to extract the source for an existing recipe. When you use this command, you must supply the root name of the recipe (i.e. no version, paths, or extensions), and you must supply the directory to which you want the source extracted.

Additional command options let you control the name of a development branch into which you can checkout the source and whether or not to keep a temporary directory, which is useful for debugging.

## 6.9.5 Synchronizing a Recipe's Extracted Source Tree

Use the `devtool sync` command to synchronize a previously extracted source tree for an existing recipe. When you use this command, you must supply the root name of the recipe (i.e. no version, paths, or extensions), and you must supply the directory to which you want the source extracted.

Additional command options let you control the name of a development branch into which you can checkout the source and whether or not to keep a temporary directory, which is useful for debugging.

## 6.9.6 Modifying an Existing Recipe

Use the `devtool modify` command to begin modifying the source of an existing recipe. This command is very similar to the [add](#) command except that it does not physically create the recipe in the workspace layer because the recipe already exists in an another layer.

The `devtool modify` command extracts the source for a recipe, sets it up as a Git repository if the source had not already been fetched from Git, checks out a branch for development, and applies any patches from the recipe as commits on top. You can use the following command to checkout the source files:

```
$ devtool modify recipe
```

Using the above command form, `devtool` uses the existing recipe's `SRC_URI` statement to locate the upstream source, extracts the source into the default sources location in the workspace. The default development branch used is "devtool".



### 6.9.7 Edit an Existing Recipe

Use the `devtool edit-recipe` command to run the default editor, which is identified using the `EDITOR` variable, on the specified recipe.

When you use the `devtool edit-recipe` command, you must supply the root name of the recipe (i.e. no version, paths, or extensions). Also, the recipe file itself must reside in the workspace as a result of the `devtool add` or `devtool upgrade` commands.

### 6.9.8 Updating a Recipe

Use the `devtool update-recipe` command to update your recipe with patches that reflect changes you make to the source files. For example, if you know you are going to work on some code, you could first use the *devtool modify* command to extract the code and set up the workspace. After which, you could modify, compile, and test the code.

When you are satisfied with the results and you have committed your changes to the Git repository, you can then run the `devtool update-recipe` to create the patches and update the recipe:

```
$ devtool update-recipe recipe
```

If you run the `devtool update-recipe` without committing your changes, the command ignores the changes.

Often, you might want to apply customizations made to your software in your own layer rather than apply them to the original recipe. If so, you can use the `-a` or `--append` option with the `devtool update-recipe` command. These options allow you to specify the layer into which to write an append file:

```
$ devtool update-recipe recipe -a base-layer-directory
```

The `*.bbappend` file is created at the appropriate path within the specified layer directory, which may or may not be in your *build/conf/bblayers.conf* file. If an append file already exists, the command updates it appropriately.

### 6.9.9 Checking on the Upgrade Status of a Recipe

Upstream recipes change over time. Consequently, you might find that you need to determine if you can upgrade a recipe to a newer version.

To check on the upgrade status of a recipe, you can use the `devtool latest-version recipe` command, which quickly shows the current version and the latest version available upstream. To get a more global picture, use the `devtool check-upgrade-status` command, which takes a list of recipes as input, or no arguments, in which case it checks all available recipes. This command will only print the recipes for which a new upstream version is available. Each such recipe will have its current version and latest upstream version, as well as the email of the maintainer and any additional information such as the commit hash or reason for not being able to upgrade it, displayed in a table.

This upgrade checking mechanism relies on the optional *UPSTREAM\_CHECK\_URI*, *UPSTREAM\_CHECK\_REGEX*, *UPSTREAM\_CHECK\_GITTAGREGEX*, *UPSTREAM\_CHECK\_COMMITS* and *UPSTREAM\_VERSION\_UNKNOWN* variables in package recipes.

**i Nota**

- Most of the time, the above variables are unnecessary. They are only required when upstream does something unusual, and default mechanisms cannot find the new upstream versions.
- For the `oe-core` layer, recipe maintainers come from the [maintainers.inc](#) file.
- If the recipe is using the [Git Fetcher \(git://\)](#) rather than a tarball, the commit hash points to the commit that matches the recipe's latest version tag, or in the absence of suitable tags, to the latest commit (when `UPSTREAM_CHECK_COMMITS` set to 1 in the recipe).

As with all `devtool` commands, you can get help on the individual command:

```
$ devtool check-upgrade-status -h
NOTE: Starting bitbake server...
usage: devtool check-upgrade-status [-h] [--all] [recipe [recipe ...]]

Prints a table of recipes together with versions currently provided by recipes,
↪and latest upstream versions, when there is a later version available

arguments:
  recipe      Name of the recipe to report (omit to report upgrade info for all
↪recipes)

options:
  -h, --help  show this help message and exit
  --all, -a   Show all recipes, not just recipes needing upgrade
```

Unless you provide a specific recipe name on the command line, the command checks all recipes in all configured layers.

Here is a partial example table that reports on all the recipes:

```
$ devtool check-upgrade-status
...
INFO: bind                      9.16.20      9.16.21      Armin Kuster
↪<akuster808@gmail.com>
INFO: inetutils                 2.1         2.2          Tom Rini
↪<trini@konsulko.com>
INFO: iproute2                 5.13.0      5.14.0      Changhyeok Bae
↪<changhyeok.bae@gmail.com>
INFO: openssl                  1.1.11      3.0.0        Alexander Kanavin
↪<alex.kanavin@gmail.com>
INFO: base-passwd              3.5.29      3.5.51      Anuj Mittal <anuj.
↪mittal@intel.com> cannot be updated due to: Version 3.5.38 requires cdebconf
↪for update-passwd utility
```

(continues on next page)

(continua dalla pagina precedente)

...

Notice the reported reason for not upgrading the `base-passwd` recipe. In this example, while a new version is available upstream, you do not want to use it because the dependency on `cdebconf` is not easily satisfied. Maintainers can explicit the reason that is shown by adding the `RECIPE_NO_UPDATE_REASON` variable to the corresponding recipe. See the `base-passwd_*.bb` recipe for an example:

```
RECIPE_NO_UPDATE_REASON = "Version 3.5.38 requires cdebconf for update-passwd_
↪utility"
```

Last but not least, you may set `UPSTREAM_VERSION_UNKNOWN` to 1 in a recipe when there's currently no way to determine its latest upstream version.

### 6.9.10 Upgrading a Recipe

As software matures, upstream recipes are upgraded to newer versions. As a developer, you need to keep your local recipes up-to-date with the upstream version releases. There are several ways of upgrading recipes. You can read about them in the "*Upgrading Recipes*" section of the Yocto Project Development Tasks Manual. This section overviews the `devtool upgrade` command.

Before you upgrade a recipe, you can check on its upgrade status. See the "*Checking on the Upgrade Status of a Recipe*" section for more information.

The `devtool upgrade` command upgrades an existing recipe to a more recent version of the recipe upstream. The command puts the upgraded recipe file along with any associated files into a "workspace" and, if necessary, extracts the source tree to a specified location. During the upgrade, patches associated with the recipe are rebased or added as needed.

When you use the `devtool upgrade` command, you must supply the root name of the recipe (i.e. no version, paths, or extensions), and you must supply the directory to which you want the source extracted. Additional command options let you control things such as the version number to which you want to upgrade (i.e. the `PV`), the source revision to which you want to upgrade (i.e. the `SRCREV`), whether or not to apply patches, and so forth.

You can read more on the `devtool upgrade` workflow in the "*Use devtool upgrade to Create a Version of the Recipe that Supports a Newer Version of the Software*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual. You can also see an example of how to use `devtool upgrade` in the "*Using devtool upgrade*" section in the Yocto Project Development Tasks Manual.

### 6.9.11 Resetting a Recipe

Use the `devtool reset` command to remove a recipe and its configuration (e.g. the corresponding `.bbappend` file) from the workspace layer. Realize that this command deletes the recipe and the append file. The command does not physically move them for you. Consequently, you must be sure to physically relocate your updated recipe and the append file outside of the workspace layer before running the `devtool reset` command.

If the `devtool reset` command detects that the recipe or the append files have been modified, the command preserves the modified files in a separate "attic" subdirectory under the workspace layer.

Here is an example that resets the workspace directory that contains the `mt-r` recipe:

```
$ devtool reset mtr
NOTE: Cleaning sysroot for recipe mtr...
NOTE: Leaving source tree /home/scottrif/bitbake-builds/build/workspace/sources/
↪mtr as-is; if you no longer need it then please delete it manually
$
```

### 6.9.12 Finish Working on a Recipe

Use the `devtool finish` command to push any committed changes to the specified recipe in the specified layer and remove it from your workspace.

This is roughly equivalent to the `devtool update-recipe` command followed by the `devtool reset` command. The changes must have been committed to the git repository created by `devtool`. Here is an example:

```
$ devtool finish recipe /path/to/custom/layer
```

### 6.9.13 Building Your Recipe

Use the `devtool build` command to build your recipe. The `devtool build` command is equivalent to the `bitbake -c populate_sysroot` command.

When you use the `devtool build` command, you must supply the root name of the recipe (i.e. do not provide versions, paths, or extensions). You can use either the `-s` or the `--disable-parallel-make` options to disable parallel makes during the build. Here is an example:

```
$ devtool build recipe
```

### 6.9.14 Building dell'Immagine

Use the `devtool build-image` command to build an image, extending it to include packages from recipes in the workspace. Using this command is useful when you want an image that ready for immediate deployment onto a device for testing. For proper integration into a final image, you need to edit your custom image recipe appropriately.

When you use the `devtool build-image` command, you must supply the name of the image. This command has no command line options:

```
$ devtool build-image image
```

### 6.9.15 Deploying Your Software on the Target Machine

Use the `devtool deploy-target` command to deploy the recipe's build output to the live target machine:

```
$ devtool deploy-target recipe target
```

The `target` is the address of the target machine, which must be running an SSH server (i.e. `user@hostname[:destdir]`).

This command deploys all files installed during the *do\_install* task. Furthermore, you do not need to have package management enabled within the target machine. If you do, the package manager is bypassed.

**Nota**

The `deploy-target` functionality is for development only. You should never use it to update an image that will be used in production.

Some conditions could prevent a deployed application from behaving as expected. When both of the following conditions are met, your application has the potential to not behave correctly when run on the target:

- You are deploying a new application to the target and the recipe you used to build the application had correctly defined runtime dependencies.
- The target does not physically have the packages on which the application depends installed.

If both of these conditions are met, your application will not behave as expected. The reason for this misbehavior is because the `devtool deploy-target` command does not deploy the packages (e.g. libraries) on which your new application depends. The assumption is that the packages are already on the target. Consequently, when a runtime call is made in the application for a dependent function (e.g. a library call), the function cannot be found.

**Avvertimento**

Runtime dependencies can be explicitly listed in the *RDEPENDS* variable, but may also be the result of a *DEPENDS* assignment in your application's recipe. This is usually the case when your application depends on libraries for compilation: these libraries are listed as build-time dependencies in the *DEPENDS* variable in your application's recipe. However these may also be runtime dependencies if they install shared objects on which your application will dynamically link to at runtime (e.g. shared libraries ending with `.so`).

These runtime dependencies are automatically resolved by the *OpenEmbedded Build System* during the packaging phase. Since `devtool` ignores packaging dependencies, they will not be installed automatically with `devtool deploy-target`.

For more information on how the *OpenEmbedded Build System* handles packaging, see the *Dipendenze di Runtime Aggiunte Automaticamente* section of the Yocto Project Overview and Concepts Manual.

To be sure you have all the dependencies local to the target, you need to be sure that the packages are pre-deployed (installed) on the target before attempting to run your application.

## 6.9.16 Removing Your Software from the Target Machine

Use the `devtool undeploy-target` command to remove deployed build output from the target machine. For the `devtool undeploy-target` command to work, you must have previously used the "*devtool deploy-target*" command:

```
$ devtool undeploy-target recipe target
```

The target is the address of the target machine, which must be running an SSH server (i.e. `user@hostname`).

### 6.9.17 Creating the Workspace Layer in an Alternative Location

Use the `devtool create-workspace` command to create a new workspace layer in your *Build Directory*. When you create a new workspace layer, it is populated with the `README` file and the `conf` directory only.

The following example creates a new workspace layer in your current working and by default names the workspace layer "workspace":

```
$ devtool create-workspace
```

You can create a workspace layer anywhere by supplying a pathname with the command. The following command creates a new workspace layer named "new-workspace":

```
$ devtool create-workspace /home/scottrif/new-workspace
```

### 6.9.18 Get the Status of the Recipes in Your Workspace

Use the `devtool status` command to list the recipes currently in your workspace. Information includes the paths to their respective external source trees.

The `devtool status` command has no command-line options:

```
$ devtool status
```

Here is sample output after using *devtool add* to create and add the `mtr_0.86.bb` recipe to the workspace directory:

```
$ devtool status
mtr:/home/scottrif/bitbake-builds/build/workspace/sources/mtr (/home/scottrif/
↪bitbake-builds/build/workspace/recipes/mtr/mtr_0.86.bb)
$
```

### 6.9.19 Search for Available Target Recipes

Use the `devtool search` command to search for available target recipes. The command matches the recipe name, package name, description, and installed files. The command displays the recipe name as a result of a match.

When you use the `devtool search` command, you must supply a keyword. The command uses the keyword when searching for a match.

Alternatively, the `devtool find-recipe` command can be used to search for recipe files instead of recipe names. Likewise, you must supply a keyword.

### 6.9.20 Get Information on Recipe Configuration Scripts

Use the `devtool configure-help` command to get help on the configuration script options for a given recipe. You must supply the recipe name to the command. For example, it shows the output of `./configure --help` for *autotools*-based recipes.

The `configure-help` command will also display the configuration options currently in use, including the ones passed through the `EXTRA_OECONF` variable.

### 6.9.21 Generate an IDE Configuration for a Recipe

The `devtool ide-sdk` automatically creates an IDE configuration and SDK to work on a given recipe. Depending on the `--mode` parameter, different types of SDKs are generated:

- `modified mode`: this creates an SDK and generates an IDE configuration in the workspace directory.
- `shared mode`: this creates a cross-compiling toolchain and the corresponding shared sysroot directories of the supplied recipe(s).

The `--target` option can be used to specify a `username@hostname` string and create a remote debugging configuration for the recipe. Similarly to `devtool deploy-target`, it requires an SSH server running on the target.

For further details on the `devtool ide-sdk` command, see the "*Using the Extensible SDK*" chapter in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

## 6.10 OpenEmbedded Kickstart (.wks) Reference

### 6.10.1 Introduzione

This chapter provides a reference on the available kickstart commands. The information lists the commands, their syntax, and meanings. Kickstart commands are based on the Fedora kickstart versions but with modifications to reflect Wic capabilities. You can see the original documentation for those commands at the following link: <https://pykickstart.readthedocs.io/en/latest/kickstart-docs.html>

### 6.10.2 Command: `part` or `partition`

Either of these commands creates a partition on the system and uses the following syntax:

```
part [mntpoint]
partition [mntpoint]
```

If you do not provide `mntpoint`, Wic creates a partition but does not mount it.

The `mntpoint` is where the partition is mounted and must be in one of the following forms:

- `/path`: For example, `/`, `/usr`, or `/home`
- `swap`: The created partition is used as swap space

Specifying a `mntpoint` causes the partition to automatically be mounted. Wic achieves this by adding entries to the filesystem table (`fstab`) during image generation. In order for Wic to generate a valid `fstab`, you must also provide one of the `--ondrive`, `--ondisk`, or `--use-uuid` partition options as part of the command.

**i Nota**

The mount program must understand the PARTUUID syntax you use with `--use-uuid` and non-root *mount-point*, including swap. The default configuration of BusyBox in OpenEmbedded supports this, but this may be disabled in custom configurations.

Here is an example that uses "/" as the mountpoint. The command uses `--ondisk` to force the partition onto the `sdb` disk:

```
part / --source rootfs --ondisk sdb --fstype=ext3 --label platform --align 1024
```

Here is a list that describes other supported options you can use with the `part` and `partition` commands:

- `--size`: The minimum partition size. Specify as an integer value optionally followed by one of the units "k" / "K" for kibibyte, "M" for mebibyte and "G" for gibibyte. The default unit if none is given is "M". You do not need this option if you use `--source`.
- `--fixed-size`: The exact partition size. Specify as an integer value optionally followed by one of the units "k" / "K" for kibibyte, "M" for mebibyte and "G" for gibibyte. The default unit if none is given is "M". Cannot be specify together with `--size`. An error occurs when assembling the disk image if the partition data is larger than `--fixed-size`.
- `--source`: This option is a Wic-specific option that names the source of the data that populates the partition. The most common value for this option is "rootfs", but you can use any value that maps to a valid source plugin. For information on the source plugins, see the "[Using the Wic Plugin Interface](#)" section in the Yocto Project Development Tasks Manual.

If you use `--source rootfs`, Wic creates a partition as large as needed and fills it with the contents of the root filesystem pointed to by the `-r` command-line option or the equivalent root filesystem derived from the `-e` command-line option. The filesystem type used to create the partition is driven by the value of the `--fstype` option specified for the partition. See the entry on `--fstype` that follows for more information.

If you use `--source plugin-name`, Wic creates a partition as large as needed and fills it with the contents of the partition that is generated by the specified plugin name using the data pointed to by the `-r` command-line option or the equivalent root filesystem derived from the `-e` command-line option. Exactly what those contents are and filesystem type used are dependent on the given plugin implementation.

If you do not use the `--source` option, the `wic` command creates an empty partition. Consequently, you must use the `--size` option to specify the size of the empty partition.

- `--ondisk` or `--ondrive`: Forces the partition to be created on a particular disk.
- `--fstype`: Sets the file system type for the partition. Valid values are:
  - `btrfs`
  - `erofs`
  - `ext2`
  - `ext3`
  - `ext4`



- squashfs
  - swap
  - vfat
- `--fsoptions`: Specifies a free-form string of options to be used when mounting the filesystem. This string is copied into the `/etc/fstab` file of the installed system and should be enclosed in quotes. If not specified, the default string is "defaults".
  - `--label label`: Specifies the label to give to the filesystem to be made on the partition. If the given label is already in use by another filesystem, a new label is created for the partition.
  - `--active`: Marks the partition as active.
  - `--align (in KBytes)`: This option is a Wic-specific option that says to start partitions on boundaries given x KBytes.
  - `--offset`: This option is a Wic-specific option that says to place a partition at exactly the specified offset. If the partition cannot be placed at the specified offset, the image build will fail. Specify as an integer value optionally followed by one of the units "s" / "S" for 512 byte sector, "k" / "K" for kibibyte, "M" for mebibyte and "G" for gibibyte. The default unit if none is given is "k".
  - `--no-table`: This option is a Wic-specific option. Using the option reserves space for the partition and causes it to become populated. However, the partition is not added to the partition table.
  - `--exclude-path`: This option is a Wic-specific option that excludes the given relative path from the resulting image. This option is only effective with the rootfs source plugin.
  - `--extra-filesystem-space`: This option is a Wic-specific option that adds extra space after the space filled by the content of the partition. The final size can exceed the size specified by the `--size` option. The default value is 10M. Specify as an integer value optionally followed by one of the units "k" / "K" for kibibyte, "M" for mebibyte and "G" for gibibyte. The default unit if none is given is "M".
  - `--extra-partition-space`: This option is a Wic-specific option that adds extra empty space after the space filled by the filesystem. With `--fixed-size` option, the extra partition space is removed from the filesystem size. Otherwise (with or without `--size` flag), the extra partition space is added to the final partition size. The default value is 0M. Specify as an integer value optionally followed by one of the units "k" / "K" for kibibyte, "M" for mebibyte and "G" for gibibyte. The default unit if none is given is "M".
  - `--overhead-factor`: This option is a Wic-specific option that multiplies the size of the partition by the option's value. You must supply a value greater than or equal to "1". The default value is "1.3".
  - `--part-name`: This option is a Wic-specific option that specifies a name for GPT partitions.
  - `--part-type`: This option is a Wic-specific option that specifies the partition type globally unique identifier (GUID) for GPT partitions. You can find the list of partition type GUIDs at [https://en.wikipedia.org/wiki/GUID\\_Partition\\_Table#Partition\\_type\\_GUIDs](https://en.wikipedia.org/wiki/GUID_Partition_Table#Partition_type_GUIDs).
  - `--use-uuid`: This option is a Wic-specific option that causes Wic to generate a random GUID for the partition. The generated identifier is used in the bootloader configuration to specify the root partition.
  - `--uuid`: This option is a Wic-specific option that specifies the partition UUID.

- `--fsuuid`: This option is a Wic-specific option that specifies the filesystem UUID. You can generate or modify *WKS\_FILE* with this option if a preconfigured filesystem UUID is added to the kernel command line in the bootloader configuration before you run Wic.
- `--system-id`: This option is a Wic-specific option that specifies the partition system ID, which is a one byte long, hexadecimal parameter with or without the 0x prefix.
- `--mkfs-extraopts`: This option specifies additional options to pass to the `mkfs` utility. Some default options for certain filesystems do not take effect. See Wic's help on kickstart (i.e. `wic help kickstart`).

### 6.10.3 Command: bootloader

This command specifies how the bootloader should be configured and supports the following options:

#### Nota

Bootloader functionality and boot partitions are implemented by the various source plugins that implement bootloader functionality. The bootloader command essentially provides a means of modifying bootloader configuration.

- `--append`: Specifies kernel parameters. These parameters will be added to the syslinux *APPEND* or grub kernel command line.
- `--configfile`: Specifies a user-defined configuration file for the bootloader. You can provide a full pathname for the file or a file located in the `files/wic` folder. This option overrides all other bootloader options.
- `--ptable`: Specifies the partition table format. Valid values are:
  - `msdos`
  - `gpt`
- `--timeout`: Specifies the number of seconds before the bootloader times out and boots the default option.

### 6.10.4 Directive: include

The `include` directive can be used to include a WKS file into another. The only argument to this command is the path to the file to include, relative to the current file. For example:

```
include common.wks.inc

bootloader --configfile="directdisk-bootloader-config.cfg"
```

## 6.11 QA Error and Warning Messages

### 6.11.1 Introduzione

When building a recipe, the OpenEmbedded build system performs various QA checks on the output to ensure that common issues are detected and reported. Sometimes when you create a new recipe to build new software, it will

build with no problems. When this is not the case, or when you have QA issues building any software, it could take a little time to resolve them.

While it is tempting to ignore a QA message or even to disable QA checks, it is best to try and resolve any reported QA issues. This chapter provides a list of the QA messages and brief explanations of the issues you could encounter so that you can properly resolve problems.

The next section provides a list of all QA error and warning messages based on a default configuration. Each entry provides the message or error form along with an explanation.

#### **Nota**

- At the end of each message, the name of the associated QA test (as listed in the "*insane*" section) appears within square brackets.
- As mentioned, this list of error and warning messages is for QA checks only. The list does not cover all possible build errors or warnings you could encounter.
- Because some QA checks are disabled by default, this list does not include all possible QA check errors and warnings.

## 6.11.2 Errors and Warnings

### **already-stripped**

```
File '<file>' from <recipe> was already stripped, this will prevent future debugging! [already-stripped]
```

Produced binaries have already been stripped prior to the build system extracting debug symbols. It is common for upstream software projects to default to stripping debug symbols for output binaries. In order for debugging to work on the target using `-dbg` packages, this stripping must be disabled.

Depending on the build system used by the software being built, disabling this stripping could be as easy as specifying an additional configure option. If not, disabling stripping might involve patching the build scripts. In the latter case, look for references to "strip" or "STRIP", or the "-s" or "-S" command-line options being specified on the linker command line (possibly through the compiler command line if preceded with "-Wl,").

#### **Nota**

Disabling stripping here does not mean that the final packaged binaries will be unstripped. Once the OpenEmbedded build system splits out debug symbols to the `-dbg` package, it will then strip the symbols from the binaries.

### **arch**

- Architecture did not match (<file\_arch>, expected <machine\_arch>) in <file> [arch]

By default, the OpenEmbedded build system checks the Executable and Linkable Format (ELF) type, bit size, and endianness of any binaries to ensure they match the target architecture. This test fails if any binaries do not match the type since there would be an incompatibility. The test could indicate that the wrong compiler

or compiler options have been used. Sometimes software, like bootloaders, might need to bypass this check. If the file you receive the error for is firmware that is not intended to be executed within the target operating system or is intended to run on a separate processor within the device, you can add "arch" to *INSANE\_SKIP* for the package. Another option is to check the *do\_compile* log and verify that the compiler options being used are correct.

- Bit size did not match (<file\_bits>, expected <machine\_bits>) in <file> [arch]

By default, the OpenEmbedded build system checks the Executable and Linkable Format (ELF) type, bit size, and endianness of any binaries to ensure they match the target architecture. This test fails if any binaries do not match the type since there would be an incompatibility. The test could indicate that the wrong compiler or compiler options have been used. Sometimes software, like bootloaders, might need to bypass this check. If the file you receive the error for is firmware that is not intended to be executed within the target operating system or is intended to run on a separate processor within the device, you can add "arch" to *INSANE\_SKIP* for the package. Another option is to check the *do\_compile* log and verify that the compiler options being used are correct.

- Endianness did not match (<file\_endianness>, expected <machine\_endianness>) in <file> [arch]

By default, the OpenEmbedded build system checks the Executable and Linkable Format (ELF) type, bit size, and endianness of any binaries to ensure they match the target architecture. This test fails if any binaries do not match the type since there would be an incompatibility. The test could indicate that the wrong compiler or compiler options have been used. Sometimes software, like bootloaders, might need to bypass this check. If the file you receive the error for is firmware that is not intended to be executed within the target operating system or is intended to run on a separate processor within the device, you can add "arch" to *INSANE\_SKIP* for the package. Another option is to check the *do\_compile* log and verify that the compiler options being used are correct.

### build-deps

```
<packagename1> rdepends on <packagename2>, but it isn't a build dependency?  
[build-deps]
```

There is a runtime dependency between the two specified packages, but there is nothing explicit within the recipe to enable the OpenEmbedded build system to ensure that dependency is satisfied. This condition is usually triggered by an *RDEPENDS* value being added at the packaging stage rather than up front, which is usually automatic based on the contents of the package. In most cases, you should change the recipe to add an explicit *RDEPENDS* for the dependency.

### buildpaths

```
File <filename> in package <packagename> contains reference to TMPDIR [buildpaths]
```

This check ensures that build system paths (including *TMPDIR*) do not appear in output files, which not only leaks build system configuration into the target, but also hinders binary reproducibility as the output will change if the build system configuration changes.

Typically these paths will enter the output through some mechanism in the configuration or compilation of the software being built by the recipe. To resolve this issue you will need to determine how the detected path is entering the

output. Sometimes it may require adjusting scripts or code to use a relative path rather than an absolute one, or to pick up the path from runtime configuration or environment variables.

#### **configure-gettext**

AM\_GNU\_GETTEXT used but no inherit gettext [configure-gettext]

If a recipe is building something that uses automake and the automake files contain an `AM_GNU_GETTEXT` directive then this check will fail if there is no `inherit gettext` statement in the recipe to ensure that gettext is available during the build. Add `inherit gettext` to remove the warning.

#### **configure-unsafe**

This autoconf log indicates errors, it looked at host include and/or library paths while determining system capabilities. Rerun configure task after fixing this.  
[configure-unsafe]

The log for the *do\_configure* task indicates that paths on the host were searched for files, which is not appropriate when cross-compiling. Look for "is unsafe for cross-compilation" or "CROSS COMPILE Badness" in the specified log file.

#### **debug-deps**

<packagename> rdepends on <debug\_packagename> [debug-deps]

There is a dependency between the specified non-dbg package (i.e. a package whose name does not end in `-dbg`) and a package that is a dbg package. The dbg packages contain debug symbols and are brought in using several different methods:

- Using the `dbg-pkgs` *IMAGE\_FEATURES* value.
- Using *IMAGE\_INSTALL*.
- As a dependency of another dbg package that was brought in using one of the above methods.

The dependency might have been automatically added because the dbg package erroneously contains files that it should not contain (e.g. a non-symlink `.so` file) or it might have been added manually (e.g. by adding to *RDEPENDS*).

#### **debug-files**

non debug package contains .debug directory: <packagename> path <path> [debug-files]

The specified package contains a `.debug` directory, which should not appear in anything but the `-dbg` package. This situation might occur if you add a path which contains a `.debug` directory and do not explicitly add the `.debug` directory to the `-dbg` package. If this is the case, add the `.debug` directory explicitly to `FILES:${PN}-dbg`. See *FILES* for additional information on *FILES*.

#### **dep-cmp**

<var>:<packagename> is invalid: <comparison> (<value>) only comparisons <, =, >, <=, and >= are allowed [dep-cmp]

If you are adding a versioned dependency relationship to one of the dependency variables (*RDEPENDS*, *RRECOMMENDS*, *RSUGGESTS*, *RPROVIDES*, *RREPLACES*, or *RCONFLICTS*), you must only use the named comparison operators. Change the versioned dependency values you are adding to match those listed in the message.

### dev-deps

```
<packagename> rdepends on <dev_packagename> [dev-deps]
```

There is a dependency between the specified non-dev package (a package whose name does not end in `-dev`) and a package that is a dev package. The dev packages contain development headers and are usually brought in using several different methods:

- Using the `dev-pkgs` *IMAGE\_FEATURES* value.
- Using *IMAGE\_INSTALL*.
- As a dependency of another dev package that was brought in using one of the above methods.

The dependency might have been automatically added (because the dev package erroneously contains files that it should not have (e.g. a non-symlink `.so` file) or it might have been added manually (e.g. by adding to *RDEPENDS*).

### desktop

```
"Desktop file issue: ... [desktop]
```

Runs the `desktop-file-validate` program against any `.desktop` files to validate their contents against the specification for `.desktop` files.

### dev-so

```
non -dev/-dbg/nativesdk- package contains symlink .so: <packagename> path '<path>' [dev-so]
```

Symlink `.so` files are for development only, and should therefore go into the `-dev` package. This situation might occur if you add `*.so*` rather than `*.so.*` to a non-dev package. Change *FILES* (and possibly *PACKAGES*) such that the specified `.so` file goes into an appropriate `-dev` package.

### empty-dirs

```
<packagename> installs files in <path>, but it is expected to be empty [empty-dirs]
```

The specified package is installing files into a directory that is normally expected to be empty (such as `/tmp`). These files may be more appropriately installed to a different location, or perhaps alternatively not installed at all, usually by updating the *do\_install* task/function.

### file-rdeps

```
<packagename> requires <files>, but no providers in its RDEPENDS [file-rdeps]
```

A file-level dependency has been identified from the specified package on the specified files, but there is no explicit corresponding entry in *RDEPENDS*. If particular files are required at runtime then *RDEPENDS* should be declared in the recipe to ensure the packages providing them are built.

### files-invalid

FILES variable for package <packagename> contains '/' which is invalid. Attempting to fix this but you should correct the metadata. [files-invalid]

The string "/" is invalid in a Unix path. Correct all occurrences where this string appears in a *FILES* variable so that there is only a single "/".

### host-user-contaminated

<package name>: <path> is owned by gid/uid <gid/uid>, which is the same as the user running bitbake. This may be due to host contamination [host-user-contaminated]

Checks that no package produced by the recipe contains any files outside of /home with a user or group ID that matches the user running BitBake. A match usually indicates that the files are being installed with an incorrect UID/GID, since target IDs are independent from host IDs. For additional information, see the section describing the *do\_install* task.

### infodir

The /usr/share/info/dir file is not meant to be shipped in a particular package. [infodir]

The /usr/share/info/dir should not be packaged. Add the following line to your *do\_install* task or to your `do_install:append` within the recipe as follows:

```
rm ${D}${infodir}/dir
```

### installed-vs-shipped

<recipe name>: Files/directories were installed but not shipped in any package [installed-vs-shipped]

Files have been installed within the *do\_install* task but have not been included in any package by way of the *FILES* variable. Files that do not appear in any package cannot be present in an image later on in the build process. You need to do one of the following:

- Add the files to *FILES* for the package you want them to appear in (e.g. `FILES:${PN}` for the main package).
- Delete the files at the end of the *do\_install* task if the files are not needed in any package.

### incompatible-license

Excluding <package> from packaging as it has incompatible license(s): <license> [incompatible-license]

Report when packages are excluded from being created due to being marked with a license that is in *INCOMPATIBLE\_LICENSE*.

**invalid-chars**

<variable> has non <encoding> characters [invalid-chars]

Checks that the recipe metadata variables *DESCRIPTION*, *SUMMARY*, *LICENSE*, and *SECTION* do not contain non-UTF-8 characters. Some package managers do not support such characters.

**invalid-packageconfig**

<package>: invalid PACKAGECONFIG(s): <configs> [invalid-packageconfig]

Checks that no undefined features are being added to *PACKAGECONFIG*. For example, any name "foo" for which the following form does not exist:

```
PACKAGECONFIG[foo] = "..."
```

**la**

<file> failed sanity test (workdir) in path <path> [la]

The specified *.la* file contains *TMPDIR* paths. Any *.la* file containing these paths is incorrect since *libtool* adds the correct sysroot prefix when using the files automatically itself.

**ldflags**

File '<file>' in package '<package>' doesn't have GNU\_HASH (didn't pass LDFLAGS?) [ldflags]

This indicates that binaries produced when building the recipe have not been linked with the *LDFLAGS* options provided by the build system. Check to be sure that the *LDFLAGS* variable is being passed to the linker command. A common workaround for this situation is to pass in *LDFLAGS* using *TARGET\_CC\_ARCH* within the recipe as follows:

```
TARGET_CC_ARCH += "${LDFLAGS}"
```

**libdir**

<packagename>: found library in wrong location [libdir]

The specified file may have been installed into an incorrect (possibly hardcoded) installation path. For example, this test will catch recipes that install */lib/bar.so* when *\${base\_libdir}* is "lib32". Another example is when recipes install */usr/lib64/foo.so* when *\${libdir}* is */usr/lib*. False positives occasionally exist. For these cases add "libdir" to *INSANE\_SKIP* for the package.

**libexec**

<packagename>: <path> is using libexec please relocate to <libexecdir> [libexec]

The specified package contains files in */usr/libexec* when the distro configuration uses a different path for <libexecdir>. By default, <libexecdir> is *\$prefix/libexec*. However, this default can be changed (e.g. *\${libdir}*).



**mime**

package contains mime types but does not inherit mime: <packagename> path '<file>' [mime]

The specified package contains mime type files (.xml files in \${datadir}/mime/packages) and yet does not inherit the *mime* class which will ensure that these get properly installed. Either add `inherit mime` to the recipe or remove the files at the *do\_install* step if they are not needed.

**mime-xdg**

package contains desktop file with key 'MimeType' but does not inherit mime-xdg: <packagename> path '<file>' [mime-xdg]

The specified package contains a .desktop file with a 'MimeType' key present, but does not inherit the *mime-xdg* class that is required in order for that to be activated. Either add `inherit mime` to the recipe or remove the files at the *do\_install* step if they are not needed.

**missing-update-alternatives**

<recipename>: recipe defines ALTERNATIVE:<packagename> but doesn't inherit update-alternatives. This might fail during do\_rootfs later! [missing-update-alternatives]

This check ensures that if a recipe sets the *ALTERNATIVE* variable that the recipe also inherits *update-alternatives* such that the alternative will be correctly set up. If you are seeing this message, either add `inherit update-alternatives` to your recipe or remove the reference to the variable if it is not needed.

**packages-list**

<packagename> is listed in PACKAGES multiple times, this leads to packaging errors. [packages-list]

Package names must appear only once in the *PACKAGES* variable. You might receive this error if you are attempting to add a package to *PACKAGES* that is already in the variable's value.

**patch-fuzz**

Fuzz detected: <patch output> [patch-fuzz]

This check looks for evidence of "fuzz" when applying patches within the *do\_patch* task. Patch fuzz is a situation when the patch tool ignores some of the context lines in order to apply the patch. Consider this example:

Patch to be applied:

```
--- filename
+++ filename
context line 1
context line 2
context line 3
+newly added line
context line 4
```

(continues on next page)

(continua dalla pagina precedente)

```
context line 5
context line 6
```

Original source code:

```
different context line 1
different context line 2
context line 3
context line 4
different context line 5
different context line 6
```

Outcome (after applying patch with fuzz):

```
different context line 1
different context line 2
context line 3
newly added line
context line 4
different context line 5
different context line 6
```

Chances are, the newly added line was actually added in a completely wrong location, or it was already in the original source and was added for the second time. This is especially possible if the context line 3 and 4 are blank or have only generic things in them, such as `#endif` or `}`. Depending on the patched code, it is entirely possible for an incorrectly patched file to still compile without errors.

### *How to eliminate patch fuzz warnings*

Use the `devtool` command as explained by the warning. First, unpack the source into devtool workspace:

```
devtool modify <recipe>
```

This will apply all of the patches, and create new commits out of them in the workspace --- with the patch context updated.

Then, replace the patches in the recipe layer:

```
devtool finish --force-patch-refresh <recipe> <layer_path>
```

The patch updates then need be reviewed (preferably with a side-by-side diff tool) to ensure they are indeed doing the right thing i.e.:

1. they are applied in the correct location within the file;
2. they do not introduce duplicate lines, or otherwise do things that are no longer necessary.

To confirm these things, you can also review the patched source code in devtool's workspace, typically in `<build_dir>/workspace/sources/<recipe>/`

Once the review is done, you can create and publish a layer commit with the patch updates that modify the context. Devtool may also refresh other things in the patches, those can be discarded.

#### **patch-status**

- Missing Upstream-Status in patch <patchfile> Please add according to <url> [patch-status]

The Upstream-Status value is missing in the specified patch file's header. This value is intended to track whether or not the patch has been sent upstream, whether or not it has been merged, etc.

For more information, see the "*Stato della Patch Upstream*" section in the Yocto Project and OpenEmbedded Contributor Guide.

- Malformed Upstream-Status in patch <patchfile> Please correct according to <url> [patch-status]

The Upstream-Status value in the specified patch file's header is invalid - it must be a specific format. See the "Missing Upstream-Status" entry above for more information.

#### **pep517-backend**

inherits setuptools3 but has pyproject.toml with <build backend>, use the correct class [pep517-backend]

Checks that a recipe inheriting *setuptools3* has a PEP517-compliant backend.

#### **perllocalpod**

<packagename> contains perllocal.pod (<files>), should not be installed [perllocalpod]

perllocal.pod is an index file of locally installed modules and so shouldn't be installed by any distribution packages. The *cpan\** class already sets NO\_PERLLOCAL to stop this file being generated by most Perl recipes, but if a recipe is using MakeMaker directly then they might not be doing this correctly. This check ensures that perllocal.pod is not in any package in order to avoid multiple packages shipping this file and thus their packages conflicting if installed together.

#### **perm-config**

Fixup Perms: invalid config line <line> [perm-config]

Reports lines in fs-perms.txt that have an invalid format.

#### **perm-line**

Fixup perms: <config> invalid line: <line> [perm-line]

Reports lines in fs-perms.txt that have an invalid format.

### perm-link

Fixup Perms: Unable to correct directory link, target already exists: <directory> -> <target> [perm-link]

Reports lines in `fs-perms.txt` that specify 'link' where the specified target already exists.

### perms

Currently, this check is unused but reserved.

### pkgconfig

<file> failed sanity test (tmpdir) in path <path> [pkgconfig]

The specified `.pc` file contains *TMPDIR*/*WORKDIR* paths. Any `.pc` file containing these paths is incorrect since `pkg-config` itself adds the correct sysroot prefix when the files are accessed.

### pkgname

<packagename> doesn't match the `[a-z0-9.+~]` regex [pkgname]

The convention within the OpenEmbedded build system (sometimes enforced by the package manager itself) is to require that package names are all lower case and to allow a restricted set of characters. If your recipe name does not match this, or you add packages to *PACKAGES* that do not conform to the convention, then you will receive this error. Rename your recipe. Or, if you have added a non-conforming package name to *PACKAGES*, change the package name appropriately.

### pkgvarcheck

- <recipefile>: Variable <variable> is set as not being package specific, please fix this. [pkgvarcheck]

Certain variables (*RDEPENDS*, *RRECOMMENDS*, *RSUGGESTS*, *RCONFLICTS*, *RPROVIDES*, *RREPLACES*, *FILES*, `pkg_preinst`, `pkg_postinst`, `pkg_prerm`, `pkg_postrm`, and *ALLOW\_EMPTY*) should always be set specific to a package (i.e. they should be set with a package name override such as `RDEPENDS:${PN} = "value"` rather than `RDEPENDS = "value"`). If you receive this error, correct any assignments to these variables within your recipe.

- recipe uses `DEPENDS:${PN}`, should use `DEPENDS` [pkgvarcheck]

This check looks for instances of setting `DEPENDS:${PN}` which is erroneous (*DEPENDS* is a recipe-wide variable and thus it is not correct to specify it for a particular package, nor will such an assignment actually work.) Set *DEPENDS* instead.

### pn-overrides

Recipe <recipefile> has PN of "<recipename>" which is in *OVERRIDES*, this can result in unexpected behavior. [pn-overrides]

The specified recipe has a name (*PN*) value that appears in *OVERRIDES*. If a recipe is named such that its *PN* value matches something already in *OVERRIDES* (e.g. *PN* happens to be the same as *MACHINE* or *DISTRO*), it can have unexpected consequences. For example, assignments such as `FILES:${PN} = "xyz"` effectively turn into `FILES`

= "xyz". Rename your recipe (or if *PN* is being set explicitly, change the *PN* value) so that the conflict does not occur. See *FILES* for additional information.

#### shebang-size

```
<package>: <file> maximum shebang size exceeded, the maximum size is 128.
[shebang-size]
```

This check ensures that the shebang line (`#!` in the first line) for a script is not longer than 128 characters, which can cause an error at runtime depending on the operating system. If you are seeing this message then the specified script may need to be patched to have a shorter in order to avoid runtime problems.

#### Shlib provider

```
<oldpackage>-<oldpkgversion> was registered as shlib provider for <library>, changing
it to <newpackage>-<newpkgversion> because it was built later
```

This message means that both `<oldpackage>` and `<newpackage>` provide the specified shared library. You can expect this message when a recipe has been renamed. However, if that is not the case, the message might indicate that a private version of a library is being erroneously picked up as the provider for a common library. If that is the case, you should add the library's `.so` filename to *PRIVATE\_LIBS* in the recipe that provides the private version of the library.

#### space-around-equal

```
<filename>:<line number> has a lack of whitespace around the assignment: '<assignment>'
```

This warning indicated that there is missing spaces around an assignment.

For example, the following assignments would print a warning:

```
FOO="bar"
FOO= "bar"
FOO ="bar"
```

These should be replaced by:

```
FOO = "bar"
```

#### src-uri-bad

- `<recipe>: SRC_URI uses unstable GitHub archives [src-uri-bad]`

GitHub provides "archive" tarballs, however these can be re-generated on the fly and thus the file's signature will not necessarily match that in the *SRC\_URI* checksums in future leading to build failures. It is recommended that you use an official release tarball or switch to pulling the corresponding revision in the actual git repository instead.

- `SRC_URI uses PN not BPN [src-uri-bad]`

If some part of *SRC\_URI* needs to reference the recipe name, it should do so using `${BPN}` rather than `${PN}` as the latter will change for different variants of the same recipe e.g. when *BBCLASSEXTEND* or *multilib* are

being used. This check will fail if a reference to `${PN}` is found within the `SRC_URI` value --- change it to `${BPN}` instead.

#### **staticdev**

```
non -staticdev package contains static .a library: <packagename> path '<path>'
[staticdev]
```

Static `.a` library files should go into a `-staticdev` package. Change *FILES* (and possibly *PACKAGES*) such that the specified `.a` file goes into an appropriate `-staticdev` package.

#### **symlink-to-sysroot**

```
Symlink <path> in <packagename> points to TMPDIR [symlink-to-sysroot]
```

The specified symlink points into *TMPDIR* on the host. Such symlinks will work on the host. However, they are clearly invalid when running on the target. You should either correct the symlink to use a relative path or remove the symlink.

#### **Recipe naming**

```
Recipe <recipe> appears native/nativesdk but is not, should inherit native/nativesdk
```

Checks that the recipe name and recipe class match, so that `*-native` recipes inherit *native* and `nativesdk-*` recipes inherit *nativesdk*.

#### **rpaths**

```
package <packagename> contains bad RPATH <rpath> in file <file> [rpaths]
```

The specified binary produced by the recipe contains dynamic library load paths (rpaths) that contain build system paths such as *TMPDIR*, which are incorrect for the target and could potentially be a security issue. Check for bad `-rpath` options being passed to the linker in your *do\_compile* log. Depending on the build system used by the software being built, there might be a configure option to disable rpath usage completely within the build of the software.

#### **textrel**

```
ELF binary '<file>' has relocations in .text [textrel]
```

The specified ELF binary contains relocations in its `.text` sections. This situation can result in a performance impact at runtime.

Typically, the way to solve this performance issue is to add `"-fPIC"` or `"-fpic"` to the compiler command-line options. For example, given software that reads *CFLAGS* when you build it, you could add the following to your recipe:

```
CFLAGS:append = " -fPIC"
```

For more information on text relocations at runtime, see <https://www.akkadia.org/drepper/textrelocs.html>.

#### unhandled-features-check

```
<recipe>: recipe doesn't inherit features_check [unhandled-features-check]
```

This check ensures that if one of the variables that the *features\_check* class supports (e.g. *REQUIRED\_DISTRO\_FEATURES*) is used, then the recipe inherits *features\_check* in order for the requirement to actually work. If you are seeing this message, either add `inherit features_check` to your recipe or remove the reference to the variable if it is not needed.

#### unimplemented-ptest

```
<tool> tests detected [unimplemented-ptest]
```

This check will detect if the source of the package contains some upstream-provided tests and, if so, that ptests are implemented for this recipe. See the "*Testing Packages With ptest*" section in the Yocto Project Test Environment Manual. See also the "*ptest*" section.

#### unknown-configure-option

```
<recipe>: configure was passed unrecognized options: <options> [unknown-configure-option]
```

The configure script is reporting that the specified options are unrecognized. This situation could be because the options were previously valid but have been removed from the configure script. Or, there was a mistake when the options were added and there is another option that should be used instead. If you are unsure, consult the upstream build documentation, the `./configure --help` output, and the upstream change log or release notes. Once you have worked out what the appropriate change is, you can update *EXTRA\_OECONF*, *PACKAGECONFIG\_CONFARGS*, or the individual *PACKAGECONFIG* option values accordingly.

#### unlisted-pkg-lics

```
LICENSE:<packagename> includes licenses (<licenses>) that are not listed in LICENSE [unlisted-pkg-lics]
```

The *LICENSE* of the recipe should be a superset of all the licenses of all packages produced by this recipe. In other words, any license in `LICENSE:*` should also appear in *LICENSE*.

#### useless-rpaths

```
<packagename>: <file> contains probably-redundant RPATH <rpath> [useless-rpaths]
```

The specified binary produced by the recipe contains dynamic library load paths (rpaths) that on a standard system are searched by default by the linker (e.g. `/lib` and `/usr/lib`). While these paths will not cause any breakage, they do waste space and are unnecessary. Depending on the build system used by the software being built, there might be a configure option to disable rpath usage completely within the build of the software.

### usrmerge

`<packagename> package is not obeying usrmerge distro feature. /<path> should be relocated to /usr. [usrmerge]`

If `usrmerge` is in *DISTRO\_FEATURES*, this check will ensure that no package installs files to root (`/bin`, `/sbin`, `/lib`, `/lib64`) directories. If you are seeing this message, it indicates that the *do\_install* step (or perhaps the build process that *do\_install* is calling into, e.g. `make install` is using hardcoded paths instead of the variables set up for this (`bindir`, `sbindir`, etc.), and should be changed so that it does.

### version-going-backwards

Package version for package `<package>` went backwards which would break package feeds (from `<version2>` to `<version1>`) `[version-going-backwards]`

If the *buildhistory* class is enabled, reports when a package being written out has a lower version than the previously written package under the same name. If you are placing output packages into a feed and upgrading packages on a target system using that feed, the version of a package going backwards can result in the target system not correctly upgrading to the "new" version of the package.

#### Nota

This is only relevant when you are using runtime package management on your target system.

### virtual-slash

`<variable>` is set to `<value>` but the substring `'virtual/'` holds no meaning in this context. It only works for build time dependencies, not runtime ones. It is suggested to use `'VIRTUAL-RUNTIME_'` variables instead. `[virtual-slash]`

`virtual/` is a convention intended for use in the build context (i.e. *PROVIDES* and *DEPENDS*) rather than the runtime context (i.e. *RPROVIDES* and *RDEPENDS*). Use *VIRTUAL-RUNTIME* variables instead for the latter.

### xorg-driver-abi

Package `<packagename>` contains Xorg driver (`<driver>`) but no `xorg-abi-` dependencies `[xorg-driver-abi]`

The specified package contains an Xorg driver, but does not have a corresponding ABI package dependency. The `xserver-xorg` recipe provides driver ABI names. All drivers should depend on the ABI versions that they have been built against. Driver recipes that include `xorg-driver-input.inc` or `xorg-driver-video.inc` will automatically get these versions. Consequently, you should only need to explicitly add dependencies to binary driver recipes.

## 6.11.3 Configuring and Disabling QA Checks

You can configure the QA checks globally so that specific check failures either raise a warning or an error message, using the *WARN\_QA* and *ERROR\_QA* variables, respectively. You can also disable checks within a particular recipe using *INSANE\_SKIP*. For information on how to work with the QA checks, see the *"insane"* section.



**i Nota**

Please keep in mind that the QA checks are meant to detect real or potential problems in the packaged output. So exercise caution when disabling these checks.

## 6.12 Immagini

The OpenEmbedded build system provides several example images to satisfy different needs. When you issue the `bitbake` command you provide a "top-level" recipe that essentially begins the build for the type of image you want.

**i Nota**

Building an image without GNU General Public License Version 3 (GPLv3), GNU Lesser General Public License Version 3 (LGPLv3), and the GNU Affero General Public License Version 3 (AGPL-3.0) components is only tested for core-image-minimal image. Furthermore, if you would like to build an image and verify that it does not include GPLv3 and similarly licensed components, you must make the following changes in the image recipe file before using the BitBake command to build the image:

```
INCOMPATIBLE_LICENSE = "GPL-3.0* LGPL-3.0"
```

Alternatively, you can adjust your distro *configuration file*, repeating and adjusting the line for all images where the license restriction must apply:

```
INCOMPATIBLE_LICENSE:pn-your-image-name = "GPL-3.0* LGPL-3.0"
```

From within the *OpenEmbedded-Core (OE-Core)* Git repository, you can use the following command to display the list of directories that contain image recipe files:

```
$ ls meta*/recipes*/images/*.bb
```

Here is a list of supported recipes:

- `build-appliance-image`: An example virtual machine that contains all the pieces required to run builds using the build system as well as the build system itself. You can boot and run the image using [VMware Workstation](#). For more information on this image, see the [Build Appliance](#) page on the Yocto Project website.
- `core-image-base`: A console-only image that fully supports the target device hardware.
- `core-image-full-cmdline`: A console-only image with more full-featured Linux system functionality installed.
- `core-image-minimal`: A small image just capable of allowing a device to boot.
- `core-image-minimal-dev`: A `core-image-minimal` image suitable for development work using the host. The image includes headers and libraries you can use in a host development environment.
- `core-image-minimal-initramfs`: A `core-image-minimal` image that has the Minimal RAM-based Initial Root Filesystem (*Initramfs*) as part of the kernel, which allows the system to find the first "init" program more efficiently. See the [PACKAGE\\_INSTALL](#) variable for additional information helpful when working with *Initramfs* images.

- `core-image-minimal-mtdutils`: A `core-image-minimal` image that has support for the Minimal MTD Utilities, which let the user interact with the MTD subsystem in the kernel to perform operations on flash devices.
- `core-image-rt`: A `core-image-minimal` image plus a real-time test suite and tools appropriate for real-time use.
- `core-image-rt-sdk`: A `core-image-rt` image that includes everything in the cross-toolchain. The image also includes development headers and libraries to form a complete stand-alone SDK and is suitable for development using the target.
- `core-image-sato`: An image with Sato support, a mobile environment and visual style that works well with mobile devices. The image supports X11 with a Sato theme and applications such as a terminal, editor, file manager, media player, and so forth.
- `core-image-sato-dev`: A `core-image-sato` image suitable for development using the host. The image includes libraries needed to build applications on the device itself, testing and profiling tools, and debug symbols. This image was formerly `core-image-sdk`.
- `core-image-sato-sdk`: A `core-image-sato` image that includes everything in the cross-toolchain. The image also includes development headers and libraries to form a complete standalone SDK and is suitable for development using the target.
- `core-image-testmaster`: A "controller" image designed to be used for automated runtime testing. Provides a "known good" image that is deployed to a separate partition so that you can boot into it and use it to deploy a second image to be tested. You can find more information about runtime testing in the "[Performing Automated Runtime Testing](#)" section in the Yocto Project Test Environment Manual.
- `core-image-testmaster-initramfs`: A RAM-based Initial Root Filesystem (*Initramfs*) image tailored for use with the `core-image-testmaster` image.
- `core-image-weston`: A very basic Wayland image with a terminal. This image provides the Wayland protocol libraries and the reference Weston compositor. For more information, see the "[Using Wayland and Weston](#)" section in the Yocto Project Development Tasks Manual.
- `core-image-x11`: A very basic X11 image with a terminal.

## 6.13 Caratteristiche

This chapter provides a reference of shipped machine and distro features you can include as part of your image, a reference on image features you can select, and a reference on [Default Features](#).

Features provide a mechanism for working out which packages should be included in the generated images. Distributions can select which features they want to support through the `DISTRO_FEATURES` variable, which is set or appended to in a distribution's configuration file such as `poky.conf`, `poky-tiny.conf`, `poky-altcfg.conf` and so forth. Machine features are set in the `MACHINE_FEATURES` variable, which is set in the machine configuration file and specifies the hardware features for a given machine.

These two variables combine to work out which kernel modules, utilities, and other packages to include. A given distribution can support a selected subset of features so some machine features might not be included if the distribution itself does not support them.

One method you can use to determine which recipes are checking to see if a particular feature is contained or not is to `grep` through the *Metadata* for the feature. Here is an example that discovers the recipes whose build is potentially changed based on a given feature:

```
$ cd openembedded-core
$ git grep 'contains.*MACHINE_FEATURES.*feature'
```

### 6.13.1 Machine Features

The items below are features you can use with *MACHINE\_FEATURES*. Features do not have a one-to-one correspondence to packages, and they can go beyond simply controlling the installation of a package or packages. Sometimes a feature can influence how certain recipes are built. For example, a feature might determine whether a particular configure option is specified within the *do\_configure* task for a particular recipe.

This feature list only represents features as shipped with the Yocto Project metadata:

- *acpi*: Hardware has ACPI (x86/x86\_64 only)
- *alsa*: Hardware has ALSA audio drivers
- *bluetooth*: Hardware has integrated BT
- *coresight*: Support for the *Coresight* Linux Kernel feature on Arm processors. This feature depends on the *opencsd* recipe which is present in the *meta-arm layer*.
- *efi*: Support for booting through EFI
- *ext2*: Hardware HDD or Microdrive
- *keyboard*: Hardware has a keyboard
- *numa*: Hardware has non-uniform memory access
- *pcbios*: Support for booting through BIOS
- *pci*: Hardware has a PCI bus
- *pcmcia*: Hardware has PCMCIA or CompactFlash sockets
- *phone*: Mobile phone (voice) support
- *qemu-usermode*: QEMU can support user-mode emulation for this machine
- *qvga*: Machine has a QVGA (320x240) display
- *rtc*: Machine has a Real-Time Clock
- *screen*: Hardware has a screen
- *serial*: Hardware has serial support (usually RS232)
- *touchscreen*: Hardware has a touchscreen
- *usb gadget*: Hardware is USB gadget device capable
- *usb host*: Hardware is USB Host capable
- *vfat*: FAT file system support

- *wifi*: Hardware has integrated WiFi

### 6.13.2 Distro Features

The items below are features you can use with *DISTRO\_FEATURES* to enable features across your distribution. Features do not have a one-to-one correspondence to packages, and they can go beyond simply controlling the installation of a package or packages. In most cases, the presence or absence of a feature translates to the appropriate option supplied to the configure script during the *do\_configure* task for the recipes that optionally support the feature. Appropriate options must be supplied, and enabling/disabling *PACKAGECONFIG* for the concerned packages is one way of supplying such options.

Some distro features are also machine features. These select features make sense to be controlled both at the machine and distribution configuration level. See the *COMBINED\_FEATURES* variable for more information.

#### Nota

*DISTRO\_FEATURES* is normally independent of kernel configuration, so if a feature specified in *DISTRO\_FEATURES* also relies on support in the kernel, you will also need to ensure that support is enabled in the kernel configuration.

This list only represents features as shipped with the Yocto Project metadata, as extra layers can define their own:

- *3g*: Include support for cellular data.
- *acl*: Include *Access Control List* support.
- *alsa*: Include *Advanced Linux Sound Architecture* support (OSS compatibility kernel modules installed if available).
- *api-documentation*: Enables generation of API documentation during recipe builds. The resulting documentation is added to SDK tarballs when the `bitbake -c populate_sdk` command is used. See the "*Adding API Documentation to the Standard SDK*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.
- *audit*: Enables *linux-audit* support.

#### Nota

The `audit` recipe is provided by *meta-oe* in *meta-openembedded*.

- *bluetooth*: Include bluetooth support (integrated BT only).
- *cramfs*: Include CramFS support.
- *debuginfod*: Include support for getting ELF debugging information through a *debuginfod* server.
- *directfb*: Include DirectFB support.
- *ext2*: Include tools for supporting devices with internal HDD/Microdrive for storing files (instead of Flash only devices).
- *gobject-introspection-data*: Include data to support *GObject Introspection*.

- *ipsec*: Include IPsec support.
- *ipv4*: Include IPv4 support.
- *ipv6*: Include IPv6 support.
- *keyboard*: Include keyboard support (e.g. keymaps will be loaded during boot).
- *minidebuginfo*: Add minimal debug symbols (*minidebuginfo*) to binary files containing, allowing `coredumpctl` and `gdb` to show symbolicated stack traces.
- *multiarch*: Enable building applications with multiple architecture support.
- *ldconfig*: Include support for `ldconfig` and `ld.so.conf` on the target.
- *lto*: Enable [Link-Time Optimisation](#).
- *nfc*: Include support for [Near Field Communication](#).
- *nfs*: Include NFS client support (for mounting NFS exports on device).
- *nls*: Include National Language Support (NLS).
- *opencl*: Include support for the [OpenCL \(Open Computing Language\)](#) framework.
- *opengl*: Include the Open Graphics Library, which is a cross-language, multi-platform application programming interface used for rendering two and three-dimensional graphics.
- *overlayfs*: Include [OverlayFS](#) support.
- *pam*: Include [Pluggable Authentication Module \(PAM\)](#) support.
- *pci*: Include PCI bus support.
- *pni-names*: Enable generation of persistent network interface names, i.e. the system tries hard to have the same but unique names for the network interfaces even after a reinstall.
- *polkit*: Include [Polkit](#) support.
- *ppp*: Include PPP dialup support.
- *ptest*: Enables building the package tests where supported by individual recipes. For more information on package tests, see the "[Testing Packages With ptest](#)" section in the Yocto Project Test Environment Manual.
- *pulseaudio*: Include support for [PulseAudio](#).
- *selinux*: Include support for [Security-Enhanced Linux \(SELinux\)](#) (requires [meta-selinux](#)).
- *seccomp*: Enables building applications with [seccomp](#) support, to allow them to strictly restrict the system calls that they are allowed to invoke.
- *smbfs*: Include SMB networks client support (for mounting Samba/Microsoft Windows shares on device).
- *systemd*: Include support for this `init` manager, which is a full replacement of for `init` with parallel starting of services, reduced shell overhead, and other features. This `init` manager is used by many distributions.
- *systemd-resolved*: Include support and use `systemd-resolved` as the main DNS name resolver in `glibc` Name Service Switch. This is a DNS resolver daemon from `systemd`.
- *usrmerge*: Merges the `/bin`, `/sbin`, `/lib`, and `/lib64` directories into their respective counterparts in the `/usr` directory to provide better package and application compatibility.

- *vfat*: Include [FAT filesystem](#) support.
- *vulkan*: Include support for the [Vulkan API](#).
- *wayland*: Include the Wayland display server protocol and the library that supports it.
- *wifi*: Include WiFi support (integrated only).
- *x11*: Include the X server and libraries.
- *xattr*: Include support for [extended file attributes](#).
- *zeroconf*: Include support for [zero configuration networking](#).

### 6.13.3 Image Features

The contents of images generated by the OpenEmbedded build system can be controlled by the [IMAGE\\_FEATURES](#) and [EXTRA\\_IMAGE\\_FEATURES](#) variables that you typically configure in your image recipes. Through these variables, you can add several different predefined packages such as development utilities or packages with debug information needed to investigate application problems or profile applications.

The image features available for all images are:

- *allow-empty-password*: Allows Dropbear and OpenSSH to accept logins from accounts having an empty password string.
- *allow-root-login*: Allows Dropbear and OpenSSH to accept root logins.
- *dbg-pkgs*: Installs debug symbol packages for all packages installed in a given image.
- *dev-pkgs*: Installs development packages (headers and extra library links) for all packages installed in a given image.
- *doc-pkgs*: Installs documentation packages for all packages installed in a given image.
- *empty-root-password*: This feature can be used if you want to allow root login with an empty password. If this feature is not present in [IMAGE\\_FEATURES](#), a non-empty password is forced in `/etc/passwd` and `/etc/shadow` if such files exist.

#### Nota

`empty-root-password` doesn't set an empty root password by itself. You get an initial empty root password thanks to the [base-passwd](#) and [shadow](#) recipes, and the presence of `empty-root-password` just disables the mechanism which forces a non-empty password for the root user.

- *lic-pkgs*: Installs license packages for all packages installed in a given image.
- *overlayfs-etc*: Configures the `/etc` directory to be in `overlayfs`. This allows to store device specific information elsewhere, especially if the root filesystem is configured to be read-only.
- *package-management*: Installs package management tools and preserves the package manager database.
- *post-install-logging*: Enables logging postinstall script runs to the `/var/log/postinstall.log` file on first boot of the image on the target system.

**i Nota**

To make the `/var/log` directory on the target persistent, remove the `files/fs-perms-volatile-log.txt` value from `FILESYSTEM_PERMS_TABLES`.

- `ptest-pkgs`: Installs `ptest` packages for all `ptest`-enabled recipes.
- `read-only-rootfs`: Creates an image whose root filesystem is read-only. See the "*Creazione di un Filesystem Root di Sola Lettura*" section in the Yocto Project Security Manual for more information.
- `read-only-rootfs-delayed-postinsts`: when specified in conjunction with `read-only-rootfs`, specifies that post-install scripts are still permitted (this assumes that the root filesystem will be made writeable for the first boot; this feature does not do anything to ensure that - it just disables the check for post-install scripts.)
- `serial-autologin-root`: when specified in conjunction with `empty-root-password` will automatically login as root on the serial console. This of course opens up a security hole if the serial console is potentially accessible to an attacker, so use with caution.
- `splash`: Enables showing a splash screen during boot. By default, this screen is provided by `psplash`, which does allow customization. If you prefer to use an alternative splash screen package, you can do so by setting the `SPLASH` variable to a different package name (or names) within the image recipe or at the distro configuration level.
- `stateless-rootfs`: specifies that the image should be created as stateless - when using `systemd`, `systemctl-native` will not be run on the image, leaving the image for population at runtime by `systemd`.
- `staticdev-pkgs`: Installs static development packages, which are static libraries (i.e. `*.a` files), for all packages installed in a given image.

Some image features are available only when you inherit the `core-image` class. The current list of these valid features is as follows:

- `hwcodecs`: Installs hardware acceleration codecs.
- `nfs-server`: Installs an NFS server.
- `perf`: Installs profiling tools such as `perf`, `systemtap`, and `LTtng`. For general information on user-space tools, see the *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)* manual.
- `ssh-server-dropbear`: Installs the Dropbear minimal SSH server.

**i Nota**

As of the 4.1 release, the `ssh-server-dropbear` feature also recommends the `openssh-sftp-server` package, which by default will be pulled into the image. This is because recent versions of the OpenSSH `scp` client now use the SFTP protocol, and thus require an SFTP server to be present to connect to. However, if you wish to use the Dropbear ssh server *without* the SFTP server installed, you can either remove `ssh-server-dropbear` from `IMAGE_FEATURES` and add `dropbear` to `IMAGE_INSTALL` instead, or alternatively still use the feature but set `BAD_RECOMMENDATIONS` as follows:

```
BAD_RECOMMENDATIONS += "openssh-sftp-server"
```

- *ssh-server-openssh*: Installs the OpenSSH SSH server, which is more full-featured than Dropbear. Note that if both the OpenSSH SSH server and the Dropbear minimal SSH server are present in *IMAGE\_FEATURES*, then OpenSSH will take precedence and Dropbear will not be installed.
- *tools-debug*: Installs debugging tools such as `strace` and `gdb`. For information on GDB, see the "*Debugging With the GNU Project Debugger (GDB) Remotely*" section in the Yocto Project Development Tasks Manual. For information on tracing and profiling, see the *Manuale di Profilazione e Tracing di Yocto Project*.
- *tools-profile*:: Installs profiling tools such as `perf`. See the *Manuale di Profilazione e Tracing di Yocto Project* for more information.
- *tools-sdk*: Installs a full SDK that runs on the device.
- *tools-testapps*: Installs device testing tools (e.g. touchscreen debugging).
- *weston*: Installs Weston (reference Wayland environment).
- *x11*: Installs the X server.
- *x11-base*: Installs the X server with a minimal environment.
- *x11-sato*: Installs the OpenedHand Sato environment.

### 6.13.4 SDK Features

The contents of a *standard* or *extensible* SDK generated by the *OpenEmbedded Build System* can be controlled by the *SDK\_FEATURES* variable that you typically configure in the image recipe for which the *do\_populate\_sdk* or *do\_populate\_sdk\_ext* task is run.

The SDK features available are:

- `go`: add *Go* utilities for building *Go*-based applications.
- `kernel-src`: adds the Linux kernel source tree to the SDK.
- `rust`: add *Rust* utilities for building *Rust*-based applications.

### 6.13.5 Default Features

Sometimes it is necessary in the *OpenEmbedded Build System* to add new functionality to *MACHINE\_FEATURES* or *DISTRO\_FEATURES*, but at the same time, allow existing distributions or machine definitions to opt out of such new features, to retain the same overall level of functionality.

To make this possible, the OpenEmbedded build system provides a default list of features through the *DISTRO\_FEATURES\_DEFAULTS* and *MACHINE\_FEATURES\_DEFAULTS* variables. You can see the default definition of these variable in the `meta/conf/distro/include/default-distrovars.inc` and `meta/conf/bitbake.conf` files.



**Nota**

This does not apply to image features (there is no `IMAGE_FEATURES_DEFAULTS` definition).

The `DISTRO_FEATURES_OPTED_OUT` and `MACHINE_FEATURES_OPTED_OUT` variables can be used to remove a feature provided by one of the `DISTRO_FEATURES_DEFAULTS` or `MACHINE_FEATURES_DEFAULTS` variables.

For example, the two following assignments:

```
DISTRO_FEATURES_DEFAULTS = "a b c"
DISTRO_FEATURES_OPTED_OUT = "b"
```

Would result in feature `a` and feature `c` making it to the final value of `DISTRO_FEATURES`, but not feature `b`. This also applies for `MACHINE_FEATURES_DEFAULTS` and `MACHINE_FEATURES_OPTED_OUT`.

You can also opt out of all default features by setting `DISTRO_FEATURES_OPTED_OUT` or `MACHINE_FEATURES_OPTED_OUT` to `*`:

```
DISTRO_FEATURES_OPTED_OUT = "*"
```

**Suggerimento**

You can verify the value of `DISTRO_FEATURES` or `MACHINE_FEATURES` with the following commands:

```
$ bitbake-getvar DISTRO_FEATURES
NOTE: Starting bitbake server...
[...]
DISTRO_FEATURES=" sysvinit      acl alsa bluetooth debuginfod ext2 ipv4 ipv6
→wifi xattr nfs zero
conf pci 3g nfc x11 vfat seccomp pulseaudio      gobject-introspection-data
→ldconfig opengl ptest mul
tiarch wayland vulkan      "
```

```
$ bitbake-getvar MACHINE_FEATURES
NOTE: Starting bitbake server...
[...]
MACHINE_FEATURES="alsa bluetooth usb gadget screen vfat rtc qemu-usermode"
```

## 6.14 Glossario delle Variabili

Questo capitolo elenca le variabili comuni utilizzate nel sistema di build OpenEmbedded e fornisce una panoramica della loro funzione e del loro contenuto.

*ABCDEFGHIJKLMNOPQRSTUVWXYZ*

### ABIEXTENSION

Estensione al campo Application Binary Interface (ABI) del nome dell'architettura canonica GNU (ad esempio, "eabi").

Le estensioni ABI vengono impostate nei file di inclusione della macchina. Ad esempio, il file `meta/conf/machine/include/arm/arch-arm.inc` imposta la seguente estensione:

```
ABIEXTENSION = "eabi"
```

### ALLOW\_EMPTY

Specifica se produrre un pacchetto di output anche se vuoto. Per default, BitBake non produce pacchetti vuoti. Questo comportamento predefinito può causare problemi quando è presente un *RDEPENDS* o altri requisiti di runtime stringenti sull'esistenza del pacchetto.

Come tutte le variabili di controllo dei pacchetti, è sempre necessario utilizzarle insieme a una sovrascrittura [override] del nome del pacchetto, come nell'esempio seguente:

```
ALLOW_EMPTY:${PN} = "1"
ALLOW_EMPTY:${PN}-dev = "1"
ALLOW_EMPTY:${PN}-staticdev = "1"
```

### ALTERNATIVE

Elenca i comandi di un pacchetto che necessitano di uno schema di denominazione binario alternativo. A volte lo stesso comando è presente in più pacchetti. In questi casi, il sistema di build OpenEmbedded deve utilizzare il sistema di alternative per creare uno schema di denominazione binario diverso, in modo che i comandi possano coesistere.

Per utilizzare la variabile, elencare i comandi del pacchetto che sono presenti anche in un altro pacchetto. Ad esempio, se il pacchetto `busybox` ha quattro comandi di questo tipo, li identifichi come segue:

```
ALTERNATIVE:busybox = "sh sed test bracket"
```

Per ulteriori informazioni sul sistema di alternative, consultare la sezione "*update-alternatives*".

### ALTERNATIVE\_LINK\_NAME

Utilizzata dal sistema di alternative per mappare i comandi duplicati alle posizioni effettive. Ad esempio, se il comando `bracket` fornito dal pacchetto `busybox` è duplicato in un altro pacchetto, è necessario utilizzare la variabile *ALTERNATIVE\_LINK\_NAME* per specificare il percorso effettivo:

```
ALTERNATIVE_LINK_NAME[bracket] = "/usr/bin/["
```

In questo esempio, il file binario per il comando `bracket` (ovvero `[`) del pacchetto `busybox` si trova in `/usr/bin/`.

#### Nota

Se *ALTERNATIVE\_LINK\_NAME* non è definito, il valore di default è `"${bindir}/name"`.

Per ulteriori informazioni sul sistema di alternative, consultare la sezione "*update-alternatives*".

### ALTERNATIVE\_PRIORITY

Utilizzato dal sistema di alternative per creare priorità predefinite per i comandi duplicati. È possibile utilizzare la variabile per creare un singolo valore di default indipendentemente dal nome del comando o dal pacchetto, un valore di default per specifici comandi duplicati indipendentemente dal pacchetto, oppure un valore di default per specifici comandi associati a determinati pacchetti. Ecco le forme di sintassi disponibili:

```
ALTERNATIVE_PRIORITY = "priority"
ALTERNATIVE_PRIORITY[name] = "priority"
ALTERNATIVE_PRIORITY_pkg[name] = "priority"
```

Per ulteriori informazioni sul sistema di alternative, consultare la sezione "[update-alternatives](#)".

### ALTERNATIVE\_TARGET

Utilizzato dal sistema di alternative per creare path di collegamento di default per i comandi duplicati. È possibile utilizzare la variabile per creare una singola posizione di default per tutti i comandi duplicati, indipendentemente dal nome del comando o dal pacchetto, una posizione di default per specifici comandi duplicati, indipendentemente dal pacchetto, oppure una posizione di default per specifici comandi associati a determinati pacchetti. Ecco le forme di sintassi disponibili:

```
ALTERNATIVE_TARGET = "target"
ALTERNATIVE_TARGET[name] = "target"
ALTERNATIVE_TARGET_pkg[name] = "target"
```

#### Nota

Se *ALTERNATIVE\_TARGET* non è definita, eredita il valore dalla variabile *ALTERNATIVE\_LINK\_NAME*.

Se *ALTERNATIVE\_LINK\_NAME* e *ALTERNATIVE\_TARGET* sono uguali, al target di *ALTERNATIVE\_TARGET* viene aggiunto ". {BPN}".

Infine, se il file a cui si fa riferimento non è stato rinominato, il sistema di alternative lo rinominerà per evitare di dover rinominare i file alternativi nel task *do\_install*, mantenendo comunque il supporto per il comando, se necessario.

Per ulteriori informazioni sul sistema di alternative, consultare la sezione "[update-alternatives](#)".

### ANY\_OF\_DISTRO\_FEATURES

Quando si eredita la classe *features\_check*, questa variabile identifica un elenco di funzionalità di distribuzione di cui almeno una deve essere abilitata nella configurazione corrente affinché il sistema di build OpenEmbedded possa compilare la ricetta. In altre parole, se nessuna delle funzionalità elencate in *ANY\_OF\_DISTRO\_FEATURES* è presente in *DISTRO\_FEATURES* nella configurazione corrente, la ricetta verrà saltata e, se il sistema di compilazione tenta di compilarla, verrà generato un errore.

### APPEND

An override list of append strings for each target specified with *LABELS*.

See the *grub-efi* class for more information on how this variable is used.

## AR

The minimal command and arguments used to run *ar*.

## ARCHIVER\_MODE

When used with the *archiver* class, determines the type of information used to create a released archive. You can use this variable to create archives of patched source, original source, configured source, and so forth by employing the following variable flags (varflags):

```
ARCHIVER_MODE[src] = "original"           # Uses original (unpacked) ↵  
↵source files.  
ARCHIVER_MODE[src] = "patched"           # Uses patched source files. ↵  
↵This is the default.  
ARCHIVER_MODE[src] = "configured"        # Uses configured source ↵  
↵files.  
ARCHIVER_MODE[diff] = "1"                # Uses patches between do_ ↵  
↵unpack and do_patch.  
ARCHIVER_MODE[diff-exclude] ?= "file file ..." # Lists files and ↵  
↵directories to exclude from diff.  
ARCHIVER_MODE[dumpdata] = "1"            # Uses environment data.  
ARCHIVER_MODE[recipe] = "1"              # Uses recipe and include ↵  
↵files.
```

For information on how the variable works, see the `meta/classes/archiver.bbclass` file in *OpenEmbedded-Core (OE-Core)*.

## AS

Minimal command and arguments needed to run the *assembler*.

## ASSUME\_PROVIDED

Lists recipe names (*PN* values) BitBake does not attempt to build. Instead, BitBake assumes these recipes have already been built.

In *OpenEmbedded-Core*, *ASSUME\_PROVIDED* mostly specifies native tools that should not be built. An example is `git-native`, which when specified, allows for the Git binary from the host to be used rather than building `git-native`.

## ASSUME\_SHLIBS

Provides additional `shlibs` provider mapping information, which adds to or overwrites the information provided automatically by the system. Separate multiple entries using spaces.

As an example, use the following form to add an `shlib` provider of `shlibname` in `packagename` with the optional version:

```
shlibname:packagename[_version]
```

Here is an example that adds a shared library named `libEGL.so.1` as being provided by the `libegl-implementation` package:

```
ASSUME_SHLIBS = "libEGL.so.1:libegl-implementation"
```

### ***AUTO\_LIBNAME\_PKGS***

When the *debian* class is inherited, which is the default behavior, *AUTO\_LIBNAME\_PKGS* specifies which packages should be checked for libraries and renamed according to Debian library package naming.

The default value is "\${PACKAGES}", which causes the *debian* class to act on all packages that are explicitly generated by the recipe.

### ***AUTO\_SYSLINUXMENU***

Enables creating an automatic menu for the syslinux bootloader. You must set this variable in your recipe. The *syslinux* class checks this variable.

### ***AUTOREV***

When *SRCREV* is set to the value of this variable, it specifies to use the latest source revision in the repository. Here is an example:

```
SRCREV = "${AUTOREV}"
```

If you use the previous statement to retrieve the latest version of software, you need to make sure *PV* contains the + sign so *bitbake* includes source control information to *PKGVS* when packaging the recipe. For example:

```
PV = "6.10.y+git"
```

For more information see the "*Automatically Incrementing a Package Version Number*" section in the Yocto Project Development Tasks Manual.

### ***AUTOTOOLS\_SCRIPT\_PATH***

When using the *autotools\** class, the *AUTOTOOLS\_SCRIPT\_PATH* variable stores the location of the different scripts used by the Autotools build system. The default value for this variable is *S*.

### ***AVAILTUNES***

The list of defined CPU and Application Binary Interface (ABI) tunings (i.e. "tunes") available for use by the OpenEmbedded build system.

The list simply presents the tunes that are available. Not all tunes may be compatible with a particular machine configuration, or with each other in a *Multilib* configuration.

To add a tune to the list, be sure to append it with spaces using the "+=" BitBake operator. Do not simply replace the list by using the "=" operator. See the "*Basic Syntax*" section in the BitBake User Manual for more information.

### ***AZ\_SAS***

Azure Storage Shared Access Signature, when using the *Azure Storage fetcher* (*az://*) This variable can be defined to be used by the fetcher to authenticate and gain access to non-public artifacts:

```
AZ_SAS = "se=2021-01-01&sp=r&sv=2018-11-09&sr=c&skoid=<skoid>&sig=<signature>"
```

For more information see Microsoft's Azure Storage documentation at <https://docs.microsoft.com/en-us/azure/storage/common/storage-sas-overview>

## B

The directory within the *Build Directory* in which the OpenEmbedded build system places generated objects during a recipe's build process. By default, this directory is the same as the *S* directory, which is defined as:

```
S = "${UNPACKDIR}/${BP}"
```

You can separate the (*S*) directory and the directory pointed to by the *B* variable. Most Autotools-based recipes support separating these directories. The build system defaults to using separate directories for `gcc` and some kernel recipes.

## BAD\_RECOMMENDATIONS

Lists "recommended-only" packages to not install. Recommended-only packages are packages installed only through the *RRECOMMENDS* variable. You can prevent any of these "recommended" packages from being installed by listing them with the *BAD\_RECOMMENDATIONS* variable:

```
BAD_RECOMMENDATIONS = "package_name package_name package_name ..."
```

You can set this variable globally in a *configuration file* or you can specify it in an image recipe directly:

```
BAD_RECOMMENDATIONS = "package_name"
```

It is important to realize that if you choose to not install packages using this variable and some other packages are dependent on them (i.e. listed in a recipe's *RDEPENDS* variable), the OpenEmbedded build system ignores your request and will install the packages to avoid dependency errors.

This variable is supported for the RPM and IPK packaging backends, but not for DEB.

See the *NO\_RECOMMENDATIONS* and the *PACKAGE\_EXCLUDE* variables for related information.

## BAREBOX\_BINARY

When using the *barebox* class, this variable allows you to specify a particular binary that should be deployed and installed.

The barebox build system can build multiple barebox binaries at once. By default, all built binaries will be deployed and installed under their original name.

Here is an example usage of this variable:

```
BAREBOX_BINARY = "barebox-boundarydevices-imx6dl-nitrogen6x-1g.img"
```

## BAREBOX\_CONFIG

When using the *barebox* class, this variable allows you to specify the name of the barebox defconfig to build. The name must be a defconfig file known to the barebox build environment. This variable is mainly useful for generic use cases where a dedicated configuration is not required. The *barebox* class itself already sets it for some QEMU machines:

```
BAREBOX_CONFIG:qemuarm = "multi_v7_defconfig"
BAREBOX_CONFIG:qemuarm64 = "multi_v8_defconfig"
BAREBOX_CONFIG:qemux86-64 = "efi_defconfig"
```

Except for these, the default value of `BAREBOX_CONFIG` is empty. For more information on how to provide a barebox configuration, see the `barebox` class.

### `BASE_LIB`

The library directory name for the CPU or Application Binary Interface (ABI) tune. The `BASE_LIB` applies only in the Multilib context. See the "*Combining Multiple Versions of Library Files into One Image*" section in the Yocto Project Development Tasks Manual for information on Multilib.

The `BASE_LIB` variable is defined in the machine include files in *OpenEmbedded-Core (OE-Core)*. If Multilib is not being used, the value defaults to "lib".

### `BASE_WORKDIR`

Points to the base of the work directory for all recipes. The default value is "\${TMPDIR}/work".

### `BB_ALLOWED_NETWORKS`

Specifies a space-delimited list of hosts that the fetcher is allowed to use to obtain the required source code. Here are considerations surrounding this variable:

- This host list is only used if `BB_NO_NETWORK` is either not set or set to "0".
- There is limited support for wildcard matching against the beginning of host names. For example, the following setting matches `git.gnu.org`, `ftp.gnu.org`, and `foo.git.gnu.org`:

```
BB_ALLOWED_NETWORKS = "*.gnu.org"
```

#### Nota

The use of the "\*" character only works at the beginning of a host name and it must be isolated from the remainder of the host name. You cannot use the wildcard character in any other location of the name or combined with the front part of the name.

For example, `*.foo.bar` is supported, while `*aa.foo.bar` is not.

- Mirrors not in the host list are skipped and logged in debug.
- Attempts to access networks not in the host list cause a failure.

Using `BB_ALLOWED_NETWORKS` in conjunction with `PREMIRRORS` is very useful. Adding the host you want to use to `PREMIRRORS` results in the source code being fetched from an allowed location and avoids raising an error when a host that is not allowed is in a `SRC_URI` statement. This is because the fetcher does not attempt to use the host listed in `SRC_URI` after a successful fetch from the `PREMIRRORS` occurs.

### `BB_BASEHASH_IGNORE_VARS`

See `BB_BASEHASH_IGNORE_VARS` in the BitBake manual.

### `BB_CACHEDIR`

See `BB_CACHEDIR` in the BitBake manual.

### `BB_CHECK_SSL_CERTS`

See `BB_CHECK_SSL_CERTS` in the BitBake manual.

### ***BB\_CONF\_FRAGMENT\_DESCRIPTION***

The *BB\_CONF\_FRAGMENT\_DESCRIPTION* variable defines the textual description of a *Configuration Fragment*. For details on how to use fragments, see the *Using Configuration Fragments* section of the Yocto Project Reference Manual.

### ***BB\_CONF\_FRAGMENT\_SUMMARY***

The *BB\_CONF\_FRAGMENT\_SUMMARY* variable defines the one-line textual summary of a *Configuration Fragment*. For details on how to use fragments, see the *Using Configuration Fragments* section of the Yocto Project Reference Manual.

### ***BB\_CONSOLELOG***

See *BB\_CONSOLELOG* in the BitBake manual.

### ***BB\_CURRENT\_MC***

See *BB\_CURRENT\_MC* in the BitBake manual.

### ***BB\_CURRENTTASK***

See *BB\_CURRENTTASK* in the BitBake manual.

### ***BB\_DEFAULT\_TASK***

See *BB\_DEFAULT\_TASK* in the BitBake manual.

### ***BB\_DEFAULT\_UMASK***

See *BB\_DEFAULT\_UMASK* in the BitBake manual.

### ***BB\_DEFER\_BBCLASSES***

See *BB\_DEFER\_BBCLASSES* in the BitBake manual.

### ***BB\_DISKMON\_DIRS***

Monitors disk space and available inodes during the build and allows you to control the build based on these parameters.

Disk space monitoring is disabled by default. To enable monitoring, add the *BB\_DISKMON\_DIRS* variable to your *build/conf/local.conf* file found in the *Build Directory*. Use the following form:

```
BB_DISKMON_DIRS = "action,dir,threshold [...]"
```

where:

action is:

|            |                                                                                                                                                                                       |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ABORT:     | Immediately stop the build when a threshold is broken.                                                                                                                                |
| STOPTASKS: | Stop the build after the currently executing tasks have finished when a threshold is broken.                                                                                          |
| WARN:      | Issue a warning but continue the build when a threshold is broken. Subsequent warnings are issued as defined by the <i>BB_DISKMON_WARNINTERVAL</i> variable, which must be defined in |

(continues on next page)



(continua dalla pagina precedente)

the `conf/local.conf` file.

`dir` is:

Any directory you choose. You can specify one or more directories to monitor by separating the groupings with a space. If two directories are on the same device, only the first directory is monitored.

`threshold` is:

Either the minimum available disk space, the minimum number of free inodes, or both. You must specify at least one. To omit one or the other, simply omit the value. Specify the threshold using G, M, K for Gbytes, Mbytes, and Kbytes, respectively. If you do not specify G, M, or K, Kbytes is assumed by default. Do not use GB, MB, or KB.

Here are some examples:

```
BB_DISKMON_DIRS = "ABORT,${TMPDIR},1G,100K WARN,${SSTATE_DIR},1G,100K"
BB_DISKMON_DIRS = "STOPTASKS,${TMPDIR},1G"
BB_DISKMON_DIRS = "ABORT,${TMPDIR},,100K"
```

The first example works only if you also provide the `BB_DISKMON_WARNINTERVAL` variable in the `build/conf/local.conf`. This example causes the build system to immediately stop when either the disk space in `${TMPDIR}` drops below 1 Gbyte or the available free inodes drops below 100 Kbytes. Because two directories are provided with the variable, the build system also issue a warning when the disk space in the `${SSTATE_DIR}` directory drops below 1 Gbyte or the number of free inodes drops below 100 Kbytes. Subsequent warnings are issued during intervals as defined by the `BB_DISKMON_WARNINTERVAL` variable.

The second example stops the build after all currently executing tasks complete when the minimum disk space in the `${TMPDIR}` directory drops below 1 Gbyte. No disk monitoring occurs for the free inodes in this case.

The final example immediately stops the build when the number of free inodes in the `${TMPDIR}` directory drops below 100 Kbytes. No disk space monitoring for the directory itself occurs in this case.

### **`BB_DISKMON_WARNINTERVAL`**

Defines the disk space and free inode warning intervals. To set these intervals, define the variable in your `build/conf/local.conf` file in the *Build Directory*.

If you are going to use the `BB_DISKMON_WARNINTERVAL` variable, you must also use the `BB_DISKMON_DIRS` variable and define its action as "WARN". During the build, subsequent warnings are issued each time disk space or number of free inodes further reduces by the respective interval.

If you do not provide a `BB_DISKMON_WARNINTERVAL` variable and you do use `BB_DISKMON_DIRS` with the "WARN" action, the disk monitoring interval defaults to the following:

```
BB_DISKMON_WARNINTERVAL = "50M, 5K"
```

When specifying the variable in your configuration file, use the following form:

```
BB_DISKMON_WARNINTERVAL = "disk_space_interval,disk_inode_interval"
```

where:

`disk_space_interval` is:

An interval of memory expressed in either  
G, M, or K for Gbytes, Mbytes, or Kbytes,  
respectively. You cannot use GB, MB, or KB.

`disk_inode_interval` is:

An interval of free inodes expressed in either  
G, M, or K for Gbytes, Mbytes, or Kbytes,  
respectively. You cannot use GB, MB, or KB.

Here is an example:

```
BB_DISKMON_DIRS = "WARN, ${SSTATE_DIR}, 1G, 100K"  
BB_DISKMON_WARNINTERVAL = "50M, 5K"
```

These variables cause the OpenEmbedded build system to issue subsequent warnings each time the available disk space further reduces by 50 Mbytes or the number of free inodes further reduces by 5 Kbytes in the `${SSTATE_DIR}` directory. Subsequent warnings based on the interval occur each time a respective interval is reached beyond the initial warning (i.e. 1 Gbytes and 100 Kbytes).

### ***BB\_ENV\_PASSTHROUGH***

See `BB_ENV_PASSTHROUGH` in the BitBake manual.

### ***BB\_ENV\_PASSTHROUGH\_ADDITIONS***

See `BB_ENV_PASSTHROUGH_ADDITIONS` in the BitBake manual.

### ***BB\_FETCH\_PREMIRRORONLY***

See `BB_FETCH_PREMIRRORONLY` in the BitBake manual.

### ***BB\_FILENAME***

See `BB_FILENAME` in the BitBake manual.

### ***BB\_GENERATE\_MIRROR\_TARBALLS***

Causes tarballs of the source control repositories (e.g. Git repositories), including metadata, to be placed in the `DL_DIR` directory.

For performance reasons, creating and placing tarballs of these repositories is not the default action by the OpenEmbedded build system:

```
BB_GENERATE_MIRROR_TARBALLS = "1"
```

Set this variable in a *configuration file*.

Once you have the tarballs containing your source files, you can clean up your *DL\_DIR* directory by deleting any Git or other source control work directories.

### ***BB\_GENERATE\_SHALLOW\_TARBALLS***

See `BB_GENERATE_SHALLOW_TARBALLS` in the BitBake manual.

### ***BB\_GIT\_DEFAULT\_DESTSUFFIX***

See `BB_GIT_DEFAULT_DESTSUFFIX` in the BitBake manual.

In *OpenEmbedded-Core (OE-Core)*, this variable is set to *BP* by default in `bitbake.conf`.

### ***BB\_GIT\_SHALLOW***

See `BB_GIT_SHALLOW` in the BitBake manual.

### ***BB\_GIT\_SHALLOW\_DEPTH***

See `BB_GIT_SHALLOW_DEPTH` in the BitBake manual.

### ***BB\_HASHCHECK\_FUNCTION***

See `BB_HASHCHECK_FUNCTION` in the BitBake manual.

### ***BB\_HASHCONFIG\_IGNORE\_VARS***

See `BB_HASHCONFIG_IGNORE_VARS` in the BitBake manual.

### ***BB\_HASHSERVE***

See `BB_HASHSERVE` in the BitBake manual.

### ***BB\_HASHSERVE\_UPSTREAM***

See `BB_HASHSERVE_UPSTREAM` in the BitBake manual.

### ***BB\_INVALIDCONF***

See `BB_INVALIDCONF` in the BitBake manual.

### ***BB\_LOADFACTOR\_MAX***

The system load threshold above which *BitBake* will stop running extra tasks.

For more information on how to limit the resources used during builds, see the *Limiting the Host Resources Usage* section of the Yocto Project Development Tasks Manual.

### ***BB\_LOGCONFIG***

See `BB_LOGCONFIG` in the BitBake manual.

### ***BB\_LOGFMT***

See `BB_LOGFMT` in the BitBake manual.

### ***BB\_MULTI\_PROVIDER\_ALLOWED***

See `BB_MULTI_PROVIDER_ALLOWED` in the BitBake manual.

### ***BB\_NICE\_LEVEL***

See `BB_NICE_LEVEL` in the BitBake manual.

### ***BB\_NO\_NETWORK***

See *BB\_NO\_NETWORK* in the BitBake manual.

### ***BB\_NUMBER\_PARSE\_THREADS***

See *BB\_NUMBER\_PARSE\_THREADS* in the BitBake manual.

### ***BB\_NUMBER\_THREADS***

The maximum number of tasks BitBake should run in parallel at any one time. The OpenEmbedded build system automatically configures this variable to be equal to the number of cores on the build system. For example, a system with a dual core processor that also uses hyper-threading causes the *BB\_NUMBER\_THREADS* variable to default to "4".

For single socket systems (i.e. one CPU), you should not have to override this variable to gain optimal parallelism during builds. However, if you have very large systems that employ multiple physical CPUs, you might want to make sure the *BB\_NUMBER\_THREADS* variable is not set higher than "20".

For more information on speeding up builds, see the "*Speeding Up a Build*" section in the Yocto Project Development Tasks Manual.

On the other hand, if your goal is to limit the amount of system resources consumed by BitBake tasks, setting *BB\_NUMBER\_THREADS* to a number lower than the number of CPU threads in your machine won't be sufficient. That's because each package will still be built and installed through a number of parallel jobs specified by the *PARALLEL\_MAKE* variable, which is by default the number of CPU threads in your system, and is not impacted by the *BB\_NUMBER\_THREADS* value.

So, if you set *BB\_NUMBER\_THREADS* to "1" but don't set *PARALLEL\_MAKE*, most of your system resources will be consumed anyway.

Therefore, if you intend to reduce the load of your build system by setting *BB\_NUMBER\_THREADS* to a relatively low value compared to the number of CPU threads on your system, you should also set *PARALLEL\_MAKE* to a similarly low value.

An alternative to using *BB\_NUMBER\_THREADS* to keep the usage of build system resources under control is to use the smarter *BB\_PRESSURE\_MAX\_CPU*, *BB\_PRESSURE\_MAX\_IO* or *BB\_PRESSURE\_MAX\_MEMORY* controls. See the *Limiting the Host Resources Usage* section of the Yocto Project Development Tasks Manual.

### ***BB\_ORIGENV***

See *BB\_ORIGENV* in the BitBake manual.

### ***BB\_PRESERVE\_ENV***

See *BB\_PRESERVE\_ENV* in the BitBake manual.

### ***BB\_PRESSURE\_MAX\_CPU***

See *BB\_PRESSURE\_MAX\_CPU* in the BitBake manual.

For more information on how to limit the resources used during builds, see the *Limiting the Host Resources Usage* section of the Yocto Project Development Tasks Manual.

### ***BB\_PRESSURE\_MAX\_IO***

See *BB\_PRESSURE\_MAX\_IO* in the BitBake manual.

For more information on how to limit the resources used during builds, see the *Limiting the Host Resources Usage* section of the Yocto Project Development Tasks Manual.

***BB\_PRESSURE\_MAX\_MEMORY***

See `BB_PRESSURE_MAX_MEMORY` in the BitBake manual.

For more information on how to limit the resources used during builds, see the *Limiting the Host Resources Usage* section of the Yocto Project Development Tasks Manual.

***BB\_RUNFMT***

See `BB_RUNFMT` in the BitBake manual.

***BB\_RUNTASK***

See `BB_RUNTASK` in the BitBake manual.

***BB\_SCHEDULER***

See `BB_SCHEDULER` in the BitBake manual.

***BB\_SCHEDULERS***

See `BB_SCHEDULERS` in the BitBake manual.

***BB\_SERVER\_TIMEOUT***

Specifies the time (in seconds) after which to unload the BitBake server due to inactivity. Set `BB_SERVER_TIMEOUT` to determine how long the BitBake server stays resident between invocations.

For example, the following statement in your `build/conf/local.conf` file instructs the server to be unloaded after 20 seconds of inactivity:

```
BB_SERVER_TIMEOUT = "20"
```

If you want the server to never be unloaded, set `BB_SERVER_TIMEOUT` to "-1".

***BB\_SETSCENE\_DEPVALID***

See `BB_SETSCENE_DEPVALID` in the BitBake manual.

***BB\_SIGNATURE\_EXCLUDE\_FLAGS***

See `BB_SIGNATURE_EXCLUDE_FLAGS` in the BitBake manual.

***BB\_SIGNATURE\_HANDLER***

See `BB_SIGNATURE_HANDLER` in the BitBake manual.

***BB\_SRCREV\_POLICY***

See `BB_SRCREV_POLICY` in the BitBake manual.

***BB\_STRICT\_CHECKSUM***

See `BB_STRICT_CHECKSUM` in the BitBake manual.

***BB\_TASK\_IONICE\_LEVEL***

See `BB_TASK_IONICE_LEVEL` in the BitBake manual.

***BB\_TASK\_NICE\_LEVEL***

See `BB_TASK_NICE_LEVEL` in the BitBake manual.

***BB\_TASKHASH***

See `BB_TASKHASH` in the BitBake manual.

***BB\_USE\_HOME\_NPMRC***

See `BB_USE_HOME_NPMRC` in the BitBake manual.

### ***BB\_VERBOSE\_LOGS***

See [BB\\_VERBOSE\\_LOGS](#) in the BitBake manual.

### ***BB\_WORKERCONTEXT***

See [BB\\_WORKERCONTEXT](#) in the BitBake manual.

### ***BBCLASSEXTEND***

Allows you to extend a recipe so that it builds variants of the software. There are common variants for recipes as "natives" like `quilt-native`, which is a copy of Quilt built to run on the build system; "crosses" such as `gcc-cross`, which is a compiler built to run on the build machine but produces binaries that run on the target *MACHINE*; "*nativesdk*", which targets the SDK machine instead of *MACHINE*; and "multilibs" in the form "`multilib:multilib_name`".

To build a different variant of the recipe with a minimal amount of code, it usually is as simple as adding the following to your recipe:

```
BBCLASSEXTEND += "native nativesdk"
BBCLASSEXTEND += "multilib:multilib_name"
```

#### **Nota**

Internally, the *BBCLASSEXTEND* mechanism generates recipe variants by rewriting variable values and applying overrides such as `:class-native`. For example, to generate a native version of a recipe, a *DEPENDS* on "foo" is rewritten to a *DEPENDS* on "foo-native".

Even when using *BBCLASSEXTEND*, the recipe is only parsed once. Parsing once adds some limitations. For example, it is not possible to include a different file depending on the variant, since `include` statements are processed when the recipe is parsed.

### ***BBDEBUG***

See [BBDEBUG](#) in the BitBake manual.

### ***BBFILE\_COLLECTIONS***

Lists the names of configured layers. These names are used to find the other `BBFILE_*` variables. Typically, each layer will append its name to this variable in its `conf/layer.conf` file.

### ***BBFILE\_PATTERN***

Variable that expands to match files from *BBFILES* in a particular layer. This variable is used in the `conf/layer.conf` file and must be suffixed with the name of the specific layer (e.g. `BBFILE_PATTERN_emenlow`).

### ***BBFILE\_PRIORITY***

Assigns the priority for recipe files in each layer.

This variable is useful in situations where the same recipe appears in more than one layer. Setting this variable allows you to prioritize a layer against other layers that contain the same recipe --- effectively letting you control the precedence for the multiple layers. The precedence established through this variable stands regardless of a recipe's version (*PV* variable). For example, a layer that has a recipe with a higher *PV* value but for which the *BBFILE\_PRIORITY* is set to have a lower precedence still has a lower precedence.

A larger value for the `BBFILE_PRIORITY` variable results in a higher precedence. For example, the value 6 has a higher precedence than the value 5. If not specified, the `BBFILE_PRIORITY` variable is set based on layer dependencies (see the `LAYERDEPENDS` variable for more information). The default priority, if unspecified for a layer with no dependencies, is the lowest defined priority + 1 (or 1 if no priorities are defined).

#### Suggestimento

You can use the command `bitbake-layers show-layers` to list all configured layers along with their priorities.

## BBFILES

A space-separated list of recipe files BitBake uses to build software.

When specifying recipe files, you can pattern match using Python's `glob` syntax. For details on the syntax, see the documentation by following the previous link.

## BBFILES\_DYNAMIC

Activates content when identified layers are present. This mechanism is commonly referred to as "dynamic layers". You identify the layers by the collections that the layers define.

Use the `BBFILES_DYNAMIC` variable to avoid `.bbappend` files whose corresponding `.bb` file is in a layer that attempts to modify other layers through `.bbappend` but does not want to introduce a hard dependency on those other layers.

Use the following form for `BBFILES_DYNAMIC`: `collection_name:filename_pattern`.

The following example identifies two collection names and two filename patterns:

```
BBFILES_DYNAMIC += " \
    clang-layer:${LAYERDIR}/dynamic-layers/meta-clang/*/*/*.bbappend \
    core:${LAYERDIR}/dynamic-layers/openembedded-core/meta/*/*/*.bbappend \
"
```

This next example shows an error message that occurs because invalid entries are found, which cause parsing to fail:

```
ERROR: BBFILES_DYNAMIC entries must be of the form <collection name>:<filename_
→pattern>, not:
    /work/my-layer/dynamic-layers/meta-security-isafw/*/*/*.bbappend
    /work/my-layer/dynamic-layers/openembedded-core/meta/*/*/*.bbappend
```

## BBINCLUDED

See `BBINCLUDED` in the BitBake manual.

## BBINCLUDELOGS

Variable that controls how BitBake displays logs on build failure.

## BBINCLUDELOGS\_LINES

If `BBINCLUDELOGS` is set, specifies the maximum number of lines from the task log file to print when reporting a failed task. If you do not set `BBINCLUDELOGS_LINES`, the entire log is printed.

## BBLAYERS

Lists the layers to enable during the build. This variable is defined in the *build/conf/bblayers.conf* configuration file in the *Build Directory*. Here is an example:

```
BBLAYERS = " \
    /home/scottrif/bitbake-builds/layers/meta \
    /home/scottrif/bitbake-builds/layers/meta-poky \
    /home/scottrif/bitbake-builds/layers/meta-yocto-bsp \
    /home/scottrif/bitbake-builds/layers/meta-mykernel \
"
```

This example enables four layers, one of which is a custom, user-defined layer named `meta-mykernel`.

## BBLAYERS\_FETCH\_DIR

See `BBLAYERS_FETCH_DIR` in the BitBake manual.

## BBMASK

Prevents BitBake from processing recipes and recipe append files.

You can use the `BBMASK` variable to "hide" these `.bb` and `.bbappend` files. BitBake ignores any recipe or recipe append files that match any of the expressions. It is as if BitBake does not see them at all. Consequently, matching files are not parsed or otherwise used by BitBake.

The values you provide are passed to Python's regular expression compiler. Consequently, the syntax follows Python's Regular Expression (re) syntax. The expressions are compared against the full paths to the files. For complete syntax information, see Python's documentation at <https://docs.python.org/3/library/re.html#regular-expression-syntax>.

The following example uses a complete regular expression to tell BitBake to ignore all recipe and recipe append files in the `meta-ti/recipes-misc/` directory:

```
BBMASK = "meta-ti/recipes-misc/"
```

If you want to mask out multiple directories or recipes, you can specify multiple regular expression fragments. This next example masks out multiple directories and individual recipes:

```
BBMASK += "/meta-ti/recipes-misc/ meta-ti/recipes-ti/packagegroup/"
BBMASK += "/meta-oe/recipes-support/"
BBMASK += "/meta-foo/.*/openldap"
BBMASK += "opencv.*\\.bbappend"
BBMASK += "lzma"
```



**i Nota**

When specifying a directory name, use the trailing slash character to ensure you match just that directory name.

**BBMULTICONFIG**

Specifies each additional separate configuration when you are building targets with multiple configurations. Use this variable in your *build/conf/local.conf* configuration file for local testing, or in a machine *configuration file*. Specify a multiconfig name for each configuration file you are using. For example, the following line specifies three configuration files:

```
BBMULTICONFIG = "configA configB configC"
```

Each configuration file you use must reside in a `multiconfig` subdirectory of a configuration directory within a layer, or within the *Build Directory* (e.g. `build_directory/conf/multiconfig/configA.conf` or `mylayer/conf/multiconfig/configB.conf`).

For information on how to use **BBMULTICONFIG** in an environment that supports building targets with multiple configurations, see the "*Building Images for Multiple Targets Using Multiple Configurations*" section in the Yocto Project Development Tasks Manual.

**BBPATH**

See **BBPATH** in the BitBake manual.

**BBSERVER**

If defined in the BitBake environment, **BBSERVER** points to the BitBake remote server.

Use the following format to export the variable to the BitBake environment:

```
export BBSERVER=localhost:$port
```

By default, **BBSERVER** also appears in **BB\_BASEHASH\_IGNORE\_VARS**. Consequently, **BBSERVER** is excluded from checksum and dependency data.

**BBTARGETS**

See **BBTARGETS** in the BitBake manual.

**BINCONFIG**

When inheriting the *binconfig-disabled* class, this variable specifies binary configuration scripts to disable in favor of using `pkg-config` to query the information. The *binconfig-disabled* class will modify the specified scripts to return an error so that calls to them can be easily found and replaced.

To add multiple scripts, separate them by spaces. Here is an example from the `libpng` recipe:

```
BINCONFIG = "${bindir}/libpng-config ${bindir}/libpng16-config"
```

**BINCONFIG\_GLOB**

When inheriting the *binconfig* class, this variable specifies a wildcard for configuration scripts that need editing. The scripts are edited to correct any paths that have been set up during compilation so that they are correct for use when installed into the sysroot and called by the build processes of other recipes.

**i Nota**

The `BINCONFIG_GLOB` variable uses [shell globbing](#), which is recognition and expansion of wildcards during pattern matching. Shell globbing is very similar to [fnmatch](#) and [glob](#).

For more information on how this variable works, see `meta/classes-recipe/binconfig.bbclass` in *OpenEmbedded-Core (OE-Core)*. You can also find general information on the class in the "*binconfig*" section.

**BITBAKE\_UI**

See `BITBAKE_UI` in the BitBake manual.

**BP**

The base recipe name and version but without any special recipe name suffix (i.e. `-native`, `lib64-`, and so forth). `BP` is comprised of the following:

```
${BPN}-${PV}
```

**BPN**

This variable is a version of the `PN` variable with common prefixes and suffixes removed, such as `nativesdk-`, `-cross`, `-native`, and multilib's `lib64-` and `lib32-`. The exact lists of prefixes and suffixes removed are specified by the `MLPREFIX` and `SPECIAL_PKGSUFFIX` variables, respectively.

**BUGTRACKER**

Specifies a URL for an upstream bug tracking website for a recipe. The OpenEmbedded build system does not use this variable. Rather, the variable is a useful pointer in case a bug in the software being built needs to be manually reported.

**BUILD\_AR**

Specifies the architecture-specific *archiver* for the build host, and its default definition is derived in part from `BUILD_PREFIX`:

```
BUILD_AR = "${BUILD_PREFIX}ar"
```

When building a *native* recipe, `AR` is set to the value of this variable by default.

The `BUILD_AR` variable should not be set manually, and is rarely used in recipes as `AR` contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the *archiver* from the build host at some point during the build.

**BUILD\_ARCH**

Specifies the architecture of the build host (e.g. `i686`). The OpenEmbedded build system sets the value of `BUILD_ARCH` from the machine name reported by the `uname` command.

**BUILD\_AS**

Specifies the architecture-specific *assembler* for the build host, and its default definition is derived in part from `BUILD_PREFIX`:

```
BUILD_AS = "${BUILD_PREFIX}as ${BUILD_AS_ARCH}"
```

When building a *native* recipe, `AS` is set to the value of this variable by default.

The `BUILD_AS` variable should not be set manually, and is rarely used in recipes as `AS` contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the `assembler` from the build host at some point during the build.

### **`BUILD_AS_ARCH`**

Specifies the architecture-specific assembler flags for the build host. By default, the value of `BUILD_AS_ARCH` is empty.

### **`BUILD_CC`**

Specifies the architecture-specific C compiler for the build host, and its default definition is derived in part from `BUILD_PREFIX` and `BUILD_CC_ARCH`:

```
BUILD_CC = "${CCACHE}${BUILD_PREFIX}gcc ${BUILD_CC_ARCH}"
```

When building a *native* recipe, `CC` is set to the value of this variable by default.

The `BUILD_CC` variable should not be set manually, and is rarely used in recipes as `CC` contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the compiler from the build host at some point during the build.

### **`BUILD_CC_ARCH`**

Specifies the architecture-specific C compiler flags for the build host. By default, the value of `BUILD_CC_ARCH` is empty.

### **`BUILD_CCLD`**

Specifies the `linker` command to be used for the build host when the C compiler is being used as the linker, and its default definition is derived in part from `BUILD_PREFIX` and `BUILD_CC_ARCH`:

```
BUILD_CCLD = "${BUILD_PREFIX}gcc ${BUILD_CC_ARCH}"
```

When building a *native* recipe, `CCLD` is set to the value of this variable by default.

The `BUILD_CCLD` variable should not be set manually, and is rarely used in recipes as `CCLD` contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the `linker` from the build host at some point during the build.

### **`BUILD_CFLAGS`**

Specifies the flags to pass to the C compiler when building for the build host. When building a *native* recipe, `CFLAGS` is set to the value of this variable by default.

### **`BUILD_CPP`**

Specifies the C preprocessor command (to both the C and the C++ compilers) when building for the build host, and its default definition is derived in part from `BUILD_PREFIX` and `BUILD_CC_ARCH`:

```
BUILD_CPP = "${BUILD_PREFIX}gcc ${BUILD_CC_ARCH} -E"
```

When building a *native* recipe, `CPP` is set to the value of this variable by default.

The `BUILD_CPP` variable should not be set manually, and is rarely used in recipes as `CPP` contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the preprocessor from the build host at some point during the build.

### ***BUILD\_CPPFLAGS***

Specifies the flags to pass to the C preprocessor (i.e. to both the C and the C++ compilers) when building for the build host. When building in the `-native` context, *CPPFLAGS* is set to the value of this variable by default.

### ***BUILD\_CXX***

Specifies the architecture-specific C++ compiler for the build host, and its default definition is derived in part from *BUILD\_PREFIX* and *BUILD\_CC\_ARCH*:

```
BUILD_CXX = "${CCACHE}${BUILD_PREFIX}g++ ${BUILD_CC_ARCH}"
```

When building a *native* recipe, *CXX* is set to the value of this variable by default.

The *BUILD\_CXX* variable should not be set manually, and is rarely used in recipes as *CXX* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the C++ compiler from the build host at some point during the build.

### ***BUILD\_CXXFLAGS***

Specifies the flags to pass to the C++ compiler when building for the build host. When building a *native* recipe, *CXXFLAGS* is set to the value of this variable by default.

### ***BUILD\_FC***

Specifies the Fortran compiler command for the build host, and its default definition is derived in part from *BUILD\_PREFIX* and *BUILD\_CC\_ARCH*:

```
BUILD_FC = "${BUILD_PREFIX}gfortran ${BUILD_CC_ARCH}"
```

When building a *native* recipe, *FC* is set to the value of this variable by default.

The *BUILD\_FC* variable should not be set manually, and is rarely used in recipes as *FC* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the Fortran compiler from the build host at some point during the build.

### ***BUILD\_LD***

Specifies the linker command for the build host, and its default definition is derived in part from *BUILD\_PREFIX* and *BUILD\_LD\_ARCH*:

```
BUILD_LD = "${BUILD_PREFIX}ld ${BUILD_LD_ARCH}"
```

When building a *native* recipe, *LD* is set to the value of this variable by default.

The *BUILD\_LD* variable should not be set manually, and is rarely used in recipes as *LD* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the linker from the build host at some point during the build.

### ***BUILD\_LD\_ARCH***

Specifies architecture-specific linker flags for the build host. By default, the value of *BUILD\_LD\_ARCH* is empty.

### ***BUILD\_LDFLAGS***

Specifies the flags to pass to the linker when building for the build host. When building a *native* recipe, *LDFLAGS* is set to the value of this variable by default.

### ***BUILD\_NM***

Specifies the architecture-specific utility to list symbols from object files for the build host, and its default definition is derived in part from *BUILD\_PREFIX*:

```
BUILD_NM = "${BUILD_PREFIX}nm"
```

When building a *native* recipe, *NM* is set to the value of this variable by default.

The *BUILD\_NM* variable should not be set manually, and is rarely used in recipes as *NM* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the utility from the build host at some point during the build.

### ***BUILD\_OBJCOPY***

Specifies the architecture-specific utility to copy object files for the build host, and its default definition is derived in part from *BUILD\_PREFIX*:

```
BUILD_OBJCOPY = "${BUILD_PREFIX}objcopy"
```

When building a *native* recipe, *OBJCOPY* is set to the value of this variable by default.

The *BUILD\_OBJCOPY* variable should not be set manually, and is rarely used in recipes as *OBJCOPY* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the utility from the build host at some point during the build.

### ***BUILD\_OBJDUMP***

Specifies the architecture-specific utility to display object files information for the build host, and its default definition is derived in part from *BUILD\_PREFIX*:

```
BUILD_OBJDUMP = "${BUILD_PREFIX}objdump"
```

When building a *native* recipe, *OBJDUMP* is set to the value of this variable by default.

The *BUILD\_OBJDUMP* variable should not be set manually, and is rarely used in recipes as *OBJDUMP* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the utility from the build host at some point during the build.

### ***BUILD\_OPTIMIZATION***

Specifies the optimization flags passed to the C compiler when building for the build host or the SDK. The flags are passed through the *BUILD\_CFLAGS* and *BUILDSDK\_CFLAGS* default values.

The default value of the *BUILD\_OPTIMIZATION* variable is "-O2 -pipe".

### ***BUILD\_OS***

Specifies the operating system in use on the build host (e.g. "linux"). The OpenEmbedded build system sets the value of *BUILD\_OS* from the OS reported by the `uname` command --- the first word, converted to lower-case characters.

### ***BUILD\_PREFIX***

The toolchain binary prefix used for native recipes. The OpenEmbedded build system uses the *BUILD\_PREFIX* value to set the *TARGET\_PREFIX* when building for *native* recipes.

### ***BUILD\_RANLIB***

Specifies the architecture-specific utility to generate indexes for archives for the build host, and its default definition is derived in part from *BUILD\_PREFIX*:

```
BUILD_RANLIB = "${BUILD_PREFIX}ranlib -D"
```

When building a *native* recipe, *RANLIB* is set to the value of this variable by default.

The *BUILD\_RANLIB* variable should not be set manually, and is rarely used in recipes as *RANLIB* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the utility from the build host at some point during the build.

### ***BUILD\_READ ELF***

Specifies the architecture-specific utility to display information about ELF files for the build host, and its default definition is derived in part from *BUILD\_PREFIX*:

```
BUILD_READ ELF = "${BUILD_PREFIX}readelf"
```

When building a *native* recipe, *READ ELF* is set to the value of this variable by default.

The *BUILD\_READ ELF* variable should not be set manually, and is rarely used in recipes as *READ ELF* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the utility from the build host at some point during the build.

### ***BUILD\_STRIP***

Specifies the command to be used to strip debugging symbols from binaries produced for the build host, and its default definition is derived in part from *BUILD\_PREFIX*:

```
BUILD_STRIP = "${BUILD_PREFIX}strip"
```

When building a *native* recipe, *STRIP* is set to the value of this variable by default.

The *BUILD\_STRIP* variable should not be set manually, and is rarely used in recipes as *STRIP* contains the appropriate value depending on the context (native or target recipes). Exception be made for target recipes that need to use the utility from the build host at some point during the build.

### ***BUILD\_SYS***

Specifies the system, including the architecture and the operating system, to use when building for the build host (i.e. when building *native* recipes).

The OpenEmbedded build system automatically sets this variable based on *BUILD\_ARCH*, *BUILD\_VENDOR*, and *BUILD\_OS*. You do not need to set the *BUILD\_SYS* variable yourself.

### ***BUILD\_VENDOR***

Specifies the vendor name to use when building for the build host. The default value is an empty string ("").

### ***BUILDDIR***

Points to the location of the *Build Directory*. You can define this directory indirectly through the *oe-init-build-env* script by passing in a *Build Directory* path when you run the script. If you run the script and do not provide a *Build Directory* path, the *BUILDDIR* defaults to `build` in the current directory.

### ***BUILDHISTORY\_COMMIT***

When inheriting the *buildhistory* class, this variable specifies whether or not to commit the build history output in a local Git repository. If set to "1", this local repository will be maintained automatically by the *buildhistory* class and a commit will be created on every build for changes to each top-level subdirectory of the build history output (images, packages, and sdk). If you want to track changes to build history over time, you should set this value to "1".

By default, the *buildhistory* class enables committing the buildhistory output in a local Git repository:

```
BUILDHISTORY_COMMIT ?= "1"
```

### ***BUILDHISTORY\_COMMIT\_AUTHOR***

When inheriting the *buildhistory* class, this variable specifies the author to use for each Git commit. In order for the *BUILDHISTORY\_COMMIT\_AUTHOR* variable to work, the *BUILDHISTORY\_COMMIT* variable must be set to "1".

Git requires that the value you provide for the *BUILDHISTORY\_COMMIT\_AUTHOR* variable takes the form of "name email@host". Providing an email address or host that is not valid does not produce an error.

By default, the *buildhistory* class sets the variable as follows:

```
BUILDHISTORY_COMMIT_AUTHOR ?= "buildhistory <buildhistory@${DISTRO}>"
```

### ***BUILDHISTORY\_DIR***

When inheriting the *buildhistory* class, this variable specifies the directory in which build history information is kept. For more information on how the variable works, see the *buildhistory* class.

By default, the *buildhistory* class sets the directory as follows:

```
BUILDHISTORY_DIR ?= "${TOPDIR}/buildhistory"
```

### ***BUILDHISTORY\_FEATURES***

When inheriting the *buildhistory* class, this variable specifies the build history features to be enabled. For more information on how build history works, see the "*Maintaining Build Output Quality with buildhistory*" section in the Yocto Project Development Tasks Manual.

You can specify these features in the form of a space-separated list:

- *image*: Analysis of the contents of images, which includes the list of installed packages among other things.
- *package*: Analysis of the contents of individual packages.
- *sdk*: Analysis of the contents of the software development kit (SDK).
- *task*: Save output file signatures for *shared state* (sstate) tasks. This saves one file per task and lists the SHA-256 checksums for each file staged (i.e. the output of the task).

By default, the *buildhistory* class enables the following features:

```
BUILDHISTORY_FEATURES ?= "image package sdk"
```

### ***BUILDHISTORY\_IMAGE\_FILES***

When inheriting the *buildhistory* class, this variable specifies a list of paths to files copied from the image contents into the build history directory under an "image-files" directory in the directory for the image, so that you can track the contents of each file. The default is to copy `/etc/passwd` and `/etc/group`, which allows you to monitor for changes in user and group entries. You can modify the list to include any file. Specifying an invalid path does not produce an error. Consequently, you can include files that might not always be present.

By default, the *buildhistory* class provides paths to the following files:

```
BUILDHISTORY_IMAGE_FILES ?= "/etc/passwd /etc/group"
```

### ***BUILDHISTORY\_PATH\_PREFIX\_STRIP***

When inheriting the *buildhistory* class, this variable specifies a common path prefix that should be stripped off the beginning of paths in the task signature list when the `task` feature is active in *BUILDHISTORY\_FEATURES*. This can be useful when build history is populated from multiple sources that may not all use the same top level directory.

By default, the *buildhistory* class sets the variable as follows:

```
BUILDHISTORY_PATH_PREFIX_STRIP ?= ""
```

In this case, no prefixes will be stripped.

### ***BUILDHISTORY\_PUSH\_REPO***

When inheriting the *buildhistory* class, this variable optionally specifies a remote repository to which build history pushes Git changes. In order for *BUILDHISTORY\_PUSH\_REPO* to work, *BUILDHISTORY\_COMMIT* must be set to "1".

The repository should correspond to a remote address that specifies a repository as understood by Git, or alternatively to a remote name that you have set up manually using `git remote` within the local repository.

By default, the *buildhistory* class sets the variable as follows:

```
BUILDHISTORY_PUSH_REPO ?= ""
```

### ***BUILDNAME***

See *BUILDNAME* in the BitBake manual.

### ***BUILDSDK\_CFLAGS***

Specifies the flags to pass to the C compiler when building for the SDK. When building in the `nativesdk-` context, *CFLAGS* is set to the value of this variable by default.

### ***BUILDSDK\_CPPFLAGS***

Specifies the flags to pass to the C pre-processor (i.e. to both the C and the C++ compilers) when building for the SDK. When building in the `nativesdk-` context, *CPPFLAGS* is set to the value of this variable by default.

### ***BUILDSDK\_CXXFLAGS***

Specifies the flags to pass to the C++ compiler when building for the SDK. When building in the `nativesdk-` context, *CXXFLAGS* is set to the value of this variable by default.



### ***BUILDSDK\_LDFLAGS***

Specifies the flags to pass to the linker when building for the SDK. When building in the `nativesdk-` context, *LD\_FLAGS* is set to the value of this variable by default.

### ***BUILDSTATS\_BASE***

Points to the location of the directory that holds build statistics when you use and enable the *buildstats* class. The *BUILDSTATS\_BASE* directory defaults to `${TMPDIR}/buildstats/`.

### ***BUSYBOX\_SPLIT\_SUID***

For the BusyBox recipe, specifies whether to split the output executable file into two parts: one for features that require `setuid root`, and one for the remaining features (i.e. those that do not require `setuid root`).

The *BUSYBOX\_SPLIT\_SUID* variable defaults to "1", which results in splitting the output executable file. Set the variable to "0" to get a single output executable file.

### ***CACHE***

Specifies the directory BitBake uses to store a cache of the *Metadata* so it does not need to be parsed every time BitBake is started.

### ***CARGO\_INSTALL\_LIBRARIES***

When inheriting the *cargo* class, the variable *CARGO\_INSTALL\_LIBRARIES* can be set to a non-empty value by individual recipes to enable the installation of the libraries the recipe has built in `${B}/target/${CARGO_TARGET_SUBDIR}` (files ending with `.so` or `.rlib`). By default this variable is not defined and libraries are not installed, to replicate the behavior of the `cargo install` command.

### ***CARGO\_PROFILE***

When inheriting the *cargo* class, the *CARGO\_PROFILE* variable allows selecting the profile to use when building (`--profile` option). By default this variable is automatically set based on the value of *DEBUG\_BUILD*.

### ***CC***

The minimal command and arguments used to run the C compiler.

### ***CCACHE\_DISABLE***

When inheriting the *ccache* class, the *CCACHE\_DISABLE* variable can be set to "1" in a recipe to disable *Ccache* support. This is useful when the recipe is known to not support it.

### ***CCACHE\_NATIVE\_RECIPES\_ALLOWED***

The *CCACHE\_NATIVE\_RECIPES\_ALLOWED* variable can be set in a *configuration file* to a list of native recipes that are allowed to be optimized with the *ccache* class.

### ***CCACHE\_TOP\_DIR***

When inheriting the *ccache* class, the *CCACHE\_TOP\_DIR* variable can be set to the location of where *Ccache* stores its cache files. This directory can be shared between builds.

### ***CCLD***

The minimal command and arguments used to run the linker when the C compiler is being used as the linker.

### ***CFLAGS***

Specifies the flags to pass to the C compiler. This variable is exported to an environment variable and thus made visible to the software being built during the compilation step.

Default initialization for *CFLAGS* varies depending on what is being built:

- `TARGET_CFLAGS` when building for the target
- `BUILD_CFLAGS` when building for the build host (i.e. `-native`)
- `BUILDSDK_CFLAGS` when building for an SDK (i.e. `nativesdk-`)

### **`CHECKLAYER_REQUIRED_TESTS`**

The `CHECKLAYER_REQUIRED_TESTS` variable lists the QA tests that are required to be enabled to pass the Yocto Project Compatible status for a layer. It is meant to be a read-only variable and any change to the variable may be done with the approval of the [Technical Steering Committee \(TSC\)](#).

For more information on the Yocto Project Compatible status, see the [Making Sure Your Layer is Compatible With Yocto Project](#) section of the Yocto Project Development Manual.

### **`CLASSOVERRIDE`**

An internal variable specifying the special class override that should currently apply (e.g. "class-target", "class-native", and so forth). The classes that use this variable (e.g. `native`, `nativesdk`, and so forth) set the variable to appropriate values.

#### **Nota**

`CLASSOVERRIDE` gets its default "class-target" value from the `bitbake.conf` file.

As an example, the following override allows you to install extra files, but only when building for the target:

```
do_install:append:class-target() {  
    install my-extra-file ${D}${sysconfdir}  
}
```

Here is an example where `FOO` is set to "native" when building for the build host, and to "other" when not building for the build host:

```
FOO:class-native = "native"  
FOO = "other"
```

The underlying mechanism behind `CLASSOVERRIDE` is simply that it is included in the default value of `OVERRIDES`.

### **`CLEANBROKEN`**

If set to "1" within a recipe, `CLEANBROKEN` specifies that the `make clean` command does not work for the software being built. Consequently, the OpenEmbedded build system will not try to run `make clean` during the `do_configure` task, which is the default behavior.

### **`COMBINED_FEATURES`**

Provides a list of hardware features that are enabled in both `MACHINE_FEATURES` and `DISTRO_FEATURES`. This select list of features contains features that make sense to be controlled both at the machine and distribution configuration level. For example, the "bluetooth" feature requires hardware support but should also be optional at the distribution level, in case the hardware supports Bluetooth but you do not ever intend to use it.

### COMMERCIAL\_AUDIO\_PLUGINS

This variable is specific to the [GStreamer recipes](#). It allows to build the GStreamer "ugly" and "bad" audio plugins.

See the *Other Variables Related to Commercial Licenses* section for usage details.

### COMMERCIAL\_VIDEO\_PLUGINS

This variable is specific to the [GStreamer recipes](#). It allows to build the GStreamer "ugly" and "bad" video plugins.

See the *Other Variables Related to Commercial Licenses* section for usage details.

### COMMON\_LICENSE\_DIR

Points to `meta/files/common-licenses` in *OpenEmbedded-Core (OE-Core)*, which is where generic license files reside.

### COMPATIBLE\_HOST

A regular expression that resolves to one or more hosts (when the recipe is native) or one or more targets (when the recipe is non-native) with which a recipe is compatible. The regular expression is matched against [HOST\\_SYS](#). You can use the variable to stop recipes from being built for classes of systems with which the recipes are not compatible. Stopping these builds is particularly useful with kernels. The variable also helps to increase parsing speed since the build system skips parsing recipes not compatible with the current system.

### COMPATIBLE\_MACHINE

A regular expression that resolves to one or more target machines with which a recipe is compatible. The regular expression is matched against [MACHINEOVERRIDES](#). You can use the variable to stop recipes from being built for machines with which the recipes are not compatible. Stopping these builds is particularly useful with kernels. The variable also helps to increase parsing speed since the build system skips parsing recipes not compatible with the current machine.

If one wants to have a recipe only available for some architectures (here `aarch64` and `mips64`), the following can be used:

```
COMPATIBLE_MACHINE = "^$"
COMPATIBLE_MACHINE:aarch64 = "^(aarch64)$"
COMPATIBLE_MACHINE:mips64 = "^(mips64)$"
```

The first line means "match all machines whose [MACHINEOVERRIDES](#) contains the empty string", which will always be none.

The second is for matching all machines whose [MACHINEOVERRIDES](#) contains one override which is exactly `aarch64`.

The third is for matching all machines whose [MACHINEOVERRIDES](#) contains one override which is exactly `mips64`.

The same could be achieved with:

```
COMPATIBLE_MACHINE = "^(aarch64|mips64)$"
```

**i Nota**

When *COMPATIBLE\_MACHINE* is set in a native recipe, the recipe is always skipped. All native recipes must be entirely target independent and should not rely on *MACHINE*.

**COMPLEMENTARY\_GLOB**

Defines wildcards to match when installing a list of complementary packages for all the packages explicitly (or implicitly) installed in an image.

The *COMPLEMENTARY\_GLOB* variable uses Unix filename pattern matching (*fnmatch*), which is similar to the Unix style pathname pattern expansion (*glob*).

The resulting list of complementary packages is associated with an item that can be added to *IMAGE\_FEATURES*. An example usage of this is the "dev-pkgs" item that when added to *IMAGE\_FEATURES* will install -dev packages (containing headers and other development files) for every package in the image.

To add a new feature item pointing to a wildcard, use a variable flag to specify the feature item name and use the value to specify the wildcard. Here is an example:

```
COMPLEMENTARY_GLOB[dev-pkgs] = '*-dev'
```

**i Nota**

When installing complementary packages, recommends relationships (set via *RRECOMMENDS*) are always ignored.

**COMPONENTS\_DIR**

Stores sysroot components provided by each recipe. The OpenEmbedded build system uses *COMPONENTS\_DIR* when constructing recipe-specific sysroots for other recipes.

The default is "\${*STAGING\_DIR*}-components." (i.e. "\${*TMPDIR*}/sysroots-components").

**CONF\_VERSION**

Tracks the version of the local configuration file (*build/conf/local.conf*). The value for *CONF\_VERSION* increments each time *build/conf/* compatibility changes.

**CONFFILES**

Identifies editable or configurable files that are part of a package. If the Package Management System (PMS) is being used to update packages on the target system, it is possible that configuration files you have changed after the original installation and that you now want to remain unchanged are overwritten. In other words, editable files might exist in the package that you do not want reset as part of the package update process. You can use the *CONFFILES* variable to list the files in the package that you wish to prevent the PMS from overwriting during this update process.

To use the *CONFFILES* variable, provide a package name override that identifies the resulting package. Then, provide a space-separated list of files. Here is an example:

```
CONFFILES:${PN} += "${sysconfdir}/file1 \
    ${sysconfdir}/file2 ${sysconfdir}/file3"
```

There is a relationship between the *CONFFILES* and *FILES* variables. The files listed within *CONFFILES* must be a subset of the files listed within *FILES*. Because the configuration files you provide with *CONFFILES* are simply being identified so that the PMS will not overwrite them, it makes sense that the files must already be included as part of the package through the *FILES* variable.

#### Nota

When specifying paths as part of the *CONFFILES* variable, it is good practice to use appropriate path variables. For example, `${sysconfdir}` rather than `/etc` or `${bindir}` rather than `/usr/bin`. You can find a list of these variables at the top of the `meta/conf/bitbake.conf` file in *OpenEmbedded-Core (OE-Core)*.

### *CONFIG\_INITRAMFS\_SOURCE*

Identifies the initial RAM filesystem (*Initramfs*) source files. The OpenEmbedded build system receives and uses this kernel Kconfig variable as an environment variable. By default, the variable is set to null ("").

The *CONFIG\_INITRAMFS\_SOURCE* can be either a single cpio archive with a `.cpio` suffix or a space-separated list of directories and files for building the *Initramfs* image. A cpio archive should contain a filesystem archive to be used as an *Initramfs* image. Directories should contain a filesystem layout to be included in the *Initramfs* image. Files should contain entries according to the format described by the `usr/gen_init_cpio` program in the kernel tree.

If you specify multiple directories and files, the *Initramfs* image will be the aggregate of all of them.

For information on creating an *Initramfs*, see the "*Building an Initial RAM Filesystem (Initramfs) Image*" section in the Yocto Project Development Tasks Manual.

### *CONFIG\_SITE*

A list of files that contains `autoconf` test results relevant to the current build. This variable is used by the Autotools utilities when running `configure`.

### *CONFIGURE\_FLAGS*

The minimal arguments for GNU `configure`.

### *CONFIGURE\_SCRIPT*

When using the *autotools\** class, the *CONFIGURE\_SCRIPT* variable stores the location of the `configure` script for the Autotools build system. The default definition for this variable is:

```
CONFIGURE_SCRIPT ?= "${AUTOTOOLS_SCRIPT_PATH}/configure"
```

Where *AUTOTOOLS\_SCRIPT\_PATH* is the location of the of the Autotools build system scripts, which defaults to *S*.

### *CONFLICT\_COMBINED\_FEATURES*

When inheriting the *features\_check* class, this variable identifies combined features (see *COMBINED\_FEATURES* for what this means) that would be in conflict should the recipe be built. In other words, if

the `CONFLICT_COMBINED_FEATURES` variable lists a feature that also appears in `COMBINED_FEATURES` within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### `CONFLICT_DISTRO_FEATURES`

When inheriting the `features_check` class, this variable identifies distro features that would be in conflict should the recipe be built. In other words, if the `CONFLICT_DISTRO_FEATURES` variable lists a feature that also appears in `DISTRO_FEATURES` within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### `CONFLICT_IMAGE_FEATURES`

When inheriting the `features_check` class, this variable identifies image features that would be in conflict should the recipe be built. In other words, if the `CONFLICT_IMAGE_FEATURES` variable lists a feature that also appears in `IMAGE_FEATURES` within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### `CONFLICT_MACHINE_FEATURES`

When inheriting the `features_check` class, this variable identifies machine features that would be in conflict should the recipe be built. In other words, if the `CONFLICT_MACHINE_FEATURES` variable lists a feature that also appears in `MACHINE_FEATURES` within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### `CONFLICT_TUNE_FEATURES`

When inheriting the `features_check` class, this variable identifies tune features that would be in conflict should the recipe be built. In other words, if the `CONFLICT_TUNE_FEATURES` variable lists a feature that also appears in `TUNE_FEATURES` within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### `CONVERSION_CMD`

This variable is used for storing image conversion commands. Image conversion can convert an image into different objects like:

- Compressed version of the image
- Checksums for the image

An example of `CONVERSION_CMD` from `image_types` class is:

```
CONVERSION_CMD:lzo = "lzo -9 ${IMAGE_NAME}${IMAGE_NAME_SUFFIX}.${type}"
```

#### `COPY_LIC_DIRS`

If set to "1" along with the `COPY_LIC_MANIFEST` variable, the OpenEmbedded build system copies into the image the license files, which are located in `/usr/share/common-licenses`, for each package. The license files are placed in directories within the image itself during build time.

#### Nota

The `COPY_LIC_DIRS` does not offer a path for adding licenses for newly installed packages to an image, which might be most suitable for read-only filesystems that cannot be upgraded. See the `LICEN-`

`SE_CREATE_PACKAGE` variable for additional information. You can also reference the "*Providing License Text*" section in the Yocto Project Development Tasks Manual for information on providing license text.

### `COPY_LIC_MANIFEST`

If set to "1", the OpenEmbedded build system copies the license manifest for the image to `/usr/share/common-licenses/license.manifest` within the image itself during build time.

#### **Nota**

The `COPY_LIC_MANIFEST` does not offer a path for adding licenses for newly installed packages to an image, which might be most suitable for read-only filesystems that cannot be upgraded. See the `LICENSE_CREATE_PACKAGE` variable for additional information. You can also reference the "*Providing License Text*" section in the Yocto Project Development Tasks Manual for information on providing license text.

### `COPYLEFT_LICENSE_EXCLUDE`

A space-separated list of licenses to exclude from the source archived by the *archiver* class. In other words, if a license in a recipe's `LICENSE` value is in the value of `COPYLEFT_LICENSE_EXCLUDE`, then its source is not archived by the class.

#### **Nota**

The `COPYLEFT_LICENSE_EXCLUDE` variable takes precedence over the `COPYLEFT_LICENSE_INCLUDE` variable.

The default value, which is "CLOSED Proprietary", for `COPYLEFT_LICENSE_EXCLUDE` is set by the *copyleft\_filter* class, which is inherited by the *archiver* class.

### `COPYLEFT_LICENSE_INCLUDE`

A space-separated list of licenses to include in the source archived by the *archiver* class. In other words, if a license in a recipe's `LICENSE` value is in the value of `COPYLEFT_LICENSE_INCLUDE`, then its source is archived by the class.

The default value is set by the *copyleft\_filter* class, which is inherited by the *archiver* class. The default value includes "GPL\*", "LGPL\*", and "AGPL\*".

### `COPYLEFT_PN_EXCLUDE`

A list of recipes to exclude in the source archived by the *archiver* class. The `COPYLEFT_PN_EXCLUDE` variable overrides the license inclusion and exclusion caused through the `COPYLEFT_LICENSE_INCLUDE` and `COPYLEFT_LICENSE_EXCLUDE` variables, respectively.

The default value, which is "" indicating to not explicitly exclude any recipes by name, for `COPYLEFT_PN_EXCLUDE` is set by the *copyleft\_filter* class, which is inherited by the *archiver* class.

### `COPYLEFT_PN_INCLUDE`

A list of recipes to include in the source archived by the *archiver* class. The `COPYLEFT_PN_INCLUDE` variable overrides the license inclusion and exclusion caused through the `COPYLEFT_LICENSE_INCLUDE` and `COPYLEFT_LICENSE_EXCLUDE` variables, respectively.



The default value, which is "" indicating to not explicitly include any recipes by name, for `COPYLEFT_PN_INCLUDE` is set by the `copyleft_filter` class, which is inherited by the `archiver` class.

### `COPYLEFT_RECIPE_TYPES`

A space-separated list of recipe types to include in the source archived by the `archiver` class. Recipe types are `target`, `native`, `nativesdk`, `cross`, `crosssdk`, and `cross-canadian`.

The default value, which is "target\*", for `COPYLEFT_RECIPE_TYPES` is set by the `copyleft_filter` class, which is inherited by the `archiver` class.

### `CORE_IMAGE_EXTRA_INSTALL`

Specifies the list of packages to be added to the image. You should set this variable in the `build/conf/local.conf` configuration file found in the *Build Directory*, or in a distro *configuration file* if your distro should always include this list of package.

This variable replaces `POKY_EXTRA_INSTALL`, which is no longer supported.

### `COREBASE`

Specifies the parent directory of the *OpenEmbedded-Core (OE-Core)* metadata layer (i.e. `meta`).

### `COREBASE_FILES`

Lists files from the `COREBASE` directory that should be copied other than the layers listed in the `build/conf/bblayers.conf` file. The `COREBASE_FILES` variable allows to copy metadata from the OpenEmbedded build system into the extensible SDK.

Explicitly listing files in `COREBASE` is needed because it typically contains build directories and other files that should not normally be copied into the extensible SDK. Consequently, the value of `COREBASE_FILES` is used in order to only copy the files that are actually needed.

### `CPP`

The minimal command and arguments used to run the C preprocessor.

### `CPPFLAGS`

Specifies the flags to pass to the C pre-processor (i.e. to both the C and the C++ compilers). This variable is exported to an environment variable and thus made visible to the software being built during the compilation step.

Default initialization for `CPPFLAGS` varies depending on what is being built:

- `TARGET_CPPFLAGS` when building for the target
- `BUILD_CPPFLAGS` when building for the build host (i.e. `-native`)
- `BUILDSDK_CPPFLAGS` when building for an SDK (i.e. `nativesdk-`)

### `CROSS_COMPILE`

The toolchain binary prefix for the target tools. The `CROSS_COMPILE` variable is the same as the `TARGET_PREFIX` variable.

#### Nota

The OpenEmbedded build system sets the `CROSS_COMPILE` variable only in certain contexts (e.g. when building for kernel and kernel module recipes).



### *CVE\_CHECK\_IGNORE*

This variable is deprecated and should be replaced by *CVE\_STATUS*.

### *CVE\_CHECK\_MANIFEST\_JSON*

When inheriting the *vex* class, this variable specifies the path to the CVE manifest in JSON format.

### *CVE\_CHECK\_SKIP\_RECIPE*

When inheriting the *vex* class, the variable specifies the list of package names (*PN*) for which CVEs (Common Vulnerabilities and Exposures) are ignored.

### *CVE\_CHECK\_STATUSMAP*

Mapping variable for all possible reasons of *CVE\_STATUS*: Patched, Unpatched and Ignored. See [meta/conf/cve-check-map.conf](#) for more details:

```
CVE_CHECK_STATUSMAP[cpe-incorrect] = "Ignored"
```

### *CVE\_CHECK\_VEX\_JUSTIFICATION*

Mapping variable for *CVE\_STATUS* reasons (for example *not-applicable-platform*) to *vex* justifications. Should be set as follows:

```
CVE_CHECK_VEX_JUSTIFICATION[not-applicable-config] = "vulnerableCodeNotPresent"
```

### *CVE\_PRODUCT*

In a recipe, defines the name used to match the recipe name against the name in the upstream NIST CVE database.

The default is `${BPN}` (except for recipes that inherit the *pypi* class where it is set based upon *PYPI\_PACKAGE*). If it does not match the name in the NIST CVE database or matches with multiple entries in the database, the default value needs to be changed.

Here is an example from the [Berkeley DB](#) recipe:

```
CVE_PRODUCT = "oracle_berkeley_db berkeley_db"
```

Sometimes the product name is not specific enough, for example "tar" has been matching CVEs for the GNU tar package and also the *node-tar* node.js extension. To avoid this problem, use the vendor name as a prefix. The syntax for this is:

```
CVE_PRODUCT = "vendor:package"
```

Since Wrynose (6.0), special characters must not be escaped. For example, the *CVE\_PRODUCT* variable for the *webkitgtk* recipe must no longer be written as *webkitgtk\+* but rather *webkitgtk+*.

### *CVE\_STATUS*

The CVE ID which is patched or should be ignored. Here is an example from the [Python3](#) recipe:

```
CVE_STATUS[CVE-2020-15523] = "not-applicable-platform: Issue only applies on ↵
↵Windows"
```

It has the format "reason: description" and the description is optional. The Reason is mapped to the final CVE state by mapping via *CVE\_CHECK\_STATUSMAP*. See [Correzione delle vulnerabilità nelle ricette](#) for details.

### CVE\_STATUS\_GROUPS

If there are many CVEs with the same status and reason, they can be simplified by using this variable instead of many similar lines with *CVE\_STATUS*:

```
CVE_STATUS_GROUPS = "CVE_STATUS_WIN CVE_STATUS_PATCHED"

CVE_STATUS_WIN = "CVE-1234-0001 CVE-1234-0002"
CVE_STATUS_WIN[status] = "not-applicable-platform: Issue only applies on ↪Windows"
CVE_STATUS_PATCHED = "CVE-1234-0003 CVE-1234-0004"
CVE_STATUS_PATCHED[status] = "fixed-version: Fixed externally"
```

### CVE\_VERSION

In a recipe, defines the version used to match the recipe version against the version in the [NIST CVE database](#) when using the *vex* or *create-spdx* class.

The default is `${PV}` but if recipes use custom version numbers which do not map to upstream software component release versions and the versions used in the CVE database, then this variable can be used to set the version number for *vex* or *create-spdx*. Example:

```
CVE_VERSION = "2.39"
```

### CXX

The minimal command and arguments used to run the C++ compiler.

### CXXFLAGS

Specifies the flags to pass to the C++ compiler. This variable is exported to an environment variable and thus made visible to the software being built during the compilation step.

Default initialization for *CXXFLAGS* varies depending on what is being built:

- *TARGET\_CXXFLAGS* when building for the target
- *BUILD\_CXXFLAGS* when building for the build host (i.e. `-native`)
- *BUILDSDK\_CXXFLAGS* when building for an SDK (i.e. `nativesdk-`)

### D

The destination directory. The location in the *Build Directory* where components are installed by the *do\_install* task. This location defaults to:

```
${WORKDIR}/image
```

#### Nota

Tasks that read from or write to this directory should run under *fakeroot*.

### DATE

The date the build was started. Dates appear using the year, month, and day (YMD) format (e.g. "20150209" for February 9th, 2015).

### DATETIME

The date and time on which the current build started. The format is suitable for timestamps.

### DEBIAN\_NOAUTONAME

When the *debian* class is inherited, which is the default behavior, *DEBIAN\_NOAUTONAME* specifies a particular package should not be renamed according to Debian library package naming. You must use the package name as an override when you set this variable. Here is an example from the `fontconfig` recipe:

```
DEBIAN_NOAUTONAME:fontconfig-utils = "1"
```

### DEBIANNAME

When the *debian* class is inherited, which is the default behavior, *DEBIANNAME* allows you to override the library name for an individual package. Overriding the library name in these cases is rare. You must use the package name as an override when you set this variable. Here is an example from the `dbus` recipe:

```
DEBIANNAME:${PN} = "dbus-1"
```

### DEBUG\_BUILD

Specifies to build packages with debugging information. This influences the value of the *SELECTED\_OPTIMIZATION* variable.

### DEBUG\_OPTIMIZATION

The options to pass in *TARGET\_CFLAGS* and *CFLAGS* when compiling a system for debugging. This variable defaults to `"-Og ${DEBUG_LEVELFLAG}"`.

### DEBUG\_PREFIX\_MAP

Allows to set C compiler options, such as `-fdebug-prefix-map`, `-fmacro-prefix-map`, and `-ffile-prefix-map`, which allow to replace build-time paths by install-time ones in the debugging sections of binaries. This makes compiler output files location independent, at the cost of having to pass an extra command to tell the debugger where source files are.

This is used by the Yocto Project to guarantee *Reproducible Builds* even when the source code of a package uses the `__FILE__` or `assert()` macros. See the [reproducible-builds.org](https://reproducible-builds.org) website for details.

This variable is set in the `meta/conf/bitbake.conf` file. It is not intended to be user-configurable.

### DEFAULT\_PREFERENCE

Specifies a weak bias for recipe selection priority.

The most common usage of this variable is to set it to `"-1"` within a recipe for a development version of a piece of software. Using the variable in this way causes the stable version of the recipe to build by default in the absence of *PREFERRED\_VERSION* being used to build the development version.

#### Nota

The bias provided by *DEFAULT\_PREFERENCE* is weak and is overridden by *BBFILE\_PRIORITY* if that variable is different between two layers that contain different versions of the same recipe.

### DEFAULT\_TIMEZONE

Specifies the time zone set in the image.

This variable causes the `tzdata` package to configure `${sysconfdir}/localtime` accordingly. Valid values are all files found in `/usr/share/zoneinfo` like `CET` or `Asia/Baku`.

### DEFAULTTUNE

The default CPU and Application Binary Interface (ABI) tunings (i.e. the "tune") used by the OpenEmbedded build system. The `DEFAULTTUNE` helps define `TUNE_FEATURES`.

The default tune is either implicitly or explicitly set by the machine (`MACHINE`). However, you can override the setting using available tunes as defined with `AVAILTUNES`.

### DEPENDS

Lists a recipe's build-time dependencies. These are dependencies on other recipes whose contents (e.g. headers and shared libraries) are needed by the recipe at build time.

As an example, consider a recipe `foo` that contains the following assignment:

```
DEPENDS = "bar"
```

The practical effect of the previous assignment is that all files installed by `bar` will be available in the appropriate staging sysroot, given by the `STAGING_DIR*` variables, by the time the `do_configure` task for `foo` runs. This mechanism is implemented by having `do_configure` depend on the `do_populate_sysroot` task of each recipe listed in `DEPENDS`, through a `[deptask]` declaration in the `base` class.

#### Nota

It seldom is necessary to reference, for example, `STAGING_DIR_HOST` explicitly. The standard classes and build-related variables are configured to automatically use the appropriate staging sysroots.

As another example, `DEPENDS` can also be used to add utilities that run on the build machine during the build. For example, a recipe that makes use of a code generator built by the recipe `codegen` might have the following:

```
DEPENDS = "codegen-native"
```

For more information, see the `native` class and the `EXTRANATIVEPATH` variable.

#### Nota

- `DEPENDS` is a list of recipe names. Or, to be more precise, it is a list of `PROVIDES` names, which usually match recipe names. Putting a package name such as `"foo-dev"` in `DEPENDS` does not make sense. Use `"foo"` instead, as this will put files from all the packages that make up `foo`, which includes those from `foo-dev`, into the sysroot.
- One recipe having another recipe in `DEPENDS` does not by itself add any runtime dependencies between the packages produced by the two recipes. However, as explained in the "*Dipendenze di Runtime Aggiunte Automaticamente*" section in the Yocto Project Overview and Concepts Manual, runtime dependencies will often be added automatically, meaning `DEPENDS` alone is sufficient for most recipes.

- Counterintuitively, *DEPENDS* is often necessary even for recipes that install precompiled components. For example, if `libfoo` is a precompiled library that links against `libbar`, then linking against `libfoo` requires both `libfoo` and `libbar` to be available in the sysroot. Without a *DEPENDS* from the recipe that installs `libfoo` to the recipe that installs `libbar`, other recipes might fail to link against `libfoo`.

For information on runtime dependencies, see the *RDEPENDS* variable. You can also see the "Tasks" and "Dependencies" sections in the BitBake User Manual for additional information on tasks and dependencies.

### DEPLOY\_DIR

Points to the general area that the OpenEmbedded build system uses to place images, packages, SDKs, and other output files that are ready to be used outside of the build system. By default, this directory resides within the *Build Directory* as `${TMPDIR}/deploy`.

For more information on the structure of the Build Directory, see "*La Directory di Build --- build/*" section. For more detail on the contents of the `deploy` directory, see the "*Immagini*", "*Feed dei Pacchetti*", and "*SDK per lo Sviluppo di Applicazioni*" sections all in the Yocto Project Overview and Concepts Manual.

#### Avvertimento

Do not confuse this variable with the similarly-named *DEPLOYDIR* variable.

### DEPLOY\_DIR\_DEB

Points to the area that the OpenEmbedded build system uses to place Debian packages that are ready to be used outside of the build system. This variable applies only when *PACKAGE\_CLASSES* contains "*package\_deb*".

The BitBake configuration file initially defines the *DEPLOY\_DIR\_DEB* variable as a sub-folder of *DEPLOY\_DIR*:

```
DEPLOY_DIR_DEB = "${DEPLOY_DIR}/deb"
```

The *package\_deb* class uses the *DEPLOY\_DIR\_DEB* variable to make sure the *do\_package\_write\_deb* task writes Debian packages into the appropriate folder. For more information on how packaging works, see the "*Feed dei Pacchetti*" section in the Yocto Project Overview and Concepts Manual.

### DEPLOY\_DIR\_IMAGE

Points to the area that the OpenEmbedded build system uses to place images and other associated output files that are ready to be deployed onto the target machine. The directory is machine-specific as it contains the `${MACHINE}` name. By default, this directory resides within the *Build Directory* as `${DEPLOY_DIR}/images/${MACHINE}/`.

It must not be used directly in recipes when deploying files. Instead, it's only useful when a recipe needs to "read" a file already deployed by a dependency. So, it should be filled with the contents of *DEPLOYDIR* by the *deploy* class or with the contents of *IMGDEPLOYDIR* by the *image* class.

For more information on the structure of the *Build Directory*, see "*La Directory di Build --- build/*" section. For more detail on the contents of the `deploy` directory, see the "*Immagini*" and "*SDK per lo Sviluppo di Applicazioni*" sections both in the Yocto Project Overview and Concepts Manual.

### DEPLOY\_DIR\_IPK

Points to the area that the OpenEmbedded build system uses to place IPK packages that are ready to be used outside of the build system. This variable applies only when *PACKAGE\_CLASSES* contains "package\_ipk".

The BitBake configuration file initially defines this variable as a sub-folder of *DEPLOY\_DIR*:

```
DEPLOY_DIR_IPK = "${DEPLOY_DIR}/ipk"
```

The *package\_ipk* class uses the *DEPLOY\_DIR\_IPK* variable to make sure the *do\_package\_write\_ipk* task writes IPK packages into the appropriate folder. For more information on how packaging works, see the "Feed dei Pacchetti" section in the Yocto Project Overview and Concepts Manual.

### DEPLOY\_DIR\_RPM

Points to the area that the OpenEmbedded build system uses to place RPM packages that are ready to be used outside of the build system. This variable applies only when *PACKAGE\_CLASSES* contains "package\_rpm".

The BitBake configuration file initially defines this variable as a sub-folder of *DEPLOY\_DIR*:

```
DEPLOY_DIR_RPM = "${DEPLOY_DIR}/rpm"
```

The *package\_rpm* class uses the *DEPLOY\_DIR\_RPM* variable to make sure the *do\_package\_write\_rpm* task writes RPM packages into the appropriate folder. For more information on how packaging works, see the "Feed dei Pacchetti" section in the Yocto Project Overview and Concepts Manual.

### DEPLOYDIR

When inheriting the *deploy* class, the *DEPLOYDIR* points to a temporary work area for deployed files that is set in the *deploy* class as follows:

```
DEPLOYDIR = "${WORKDIR}/deploy-${PN}"
```

Recipes inheriting the *deploy* class should copy files to be deployed into *DEPLOYDIR*, and the class will take care of copying them into *DEPLOY\_DIR\_IMAGE* afterwards.

#### Avvertimento

Do not confuse this variable with the similarly-named *DEPLOY\_DIR* variable.

### DESCRIPTION

The package description used by package managers. If not set, *DESCRIPTION* takes the value of the *SUMMARY* variable.

### DEV\_PKG\_DEPENDENCY

Provides an easy way for recipes to disable or adjust the runtime recommendation (*RRECOMMENDS*) of the *\${PN}-dev* package on the main (*\${PN}*) package.

### DISABLE\_STATIC

Used in order to disable static linking by default (in order to save space, since static libraries are often unused in embedded systems.) The default value is " --disable-static", however it can be set to "" in order to enable static linking if desired. Certain recipes do this individually, and also there is a `meta/conf/distro/include/`

`no-static-libs.inc` include file that disables static linking for a number of recipes. Some software packages or build tools (such as CMake) have explicit support for enabling / disabling static linking, and in those cases `DISABLE_STATIC` is not used.

## ***DISTRO***

The short name of the distribution. For information on the long name of the distribution, see the `DISTRO_NAME` variable.

You can define the `DISTRO` in two ways:

- with the `distro/` fragment:

```
$ bitbake-config-build enable-fragment distro/<DISTRO>
```

Replace `<DISTRO>` with the name of the distro in the above command.

- in the `build/conf/local.conf` file found in the *Build Directory*.

The `DISTRO` variable corresponds to a distribution configuration file whose root name is the same as the variable's argument and whose filename extension is `.conf`. For example, the distribution configuration file for the Poky distribution is named `poky.conf` and resides in the `meta-poky/conf/distro` directory of `meta-poky`.

Within that `poky.conf` file, the `DISTRO` variable is set as follows:

```
DISTRO = "poky"
```

Distribution configuration files are located in a `conf/distro` directory within the *Metadata* that contains the distribution configuration. The value for `DISTRO` must not contain spaces, and is typically all lower-case.

### ***i* Nota**

If the `DISTRO` variable is blank, a set of default configurations are used, which are specified within `meta/conf/distro/defaultsetup.conf` also in *OpenEmbedded-Core (OE-Core)*.

## ***DISTRO\_CODENAME***

Specifies a codename for the distribution being built.

## ***DISTRO\_EXTRA\_RDEPENDS***

Specifies a list of distro-specific packages to add to all images. This variable takes effect through `packagegroup-base` so the variable only really applies to the more full-featured images that include `packagegroup-base`. You can use this variable to keep distro policy out of generic images. As with all other distro variables, you set this variable in the distro `.conf` file.

## ***DISTRO\_EXTRA\_RRECOMMENDS***

Specifies a list of distro-specific packages to add to all images if the packages exist. The packages might not exist or be empty (e.g. kernel modules). The list of packages are automatically installed but you can remove them.

## ***DISTRO\_FEATURES***

The software support you want in your distribution for various features. You define your distribution features in the distribution configuration file.

In most cases, the presence or absence of a feature in ***DISTRO\_FEATURES*** is translated to the appropriate option supplied to the configure script during the ***do\_configure*** task for recipes that optionally support the feature. For example, specifying "x11" in ***DISTRO\_FEATURES***, causes every piece of software built for the target that can optionally support X11 to have its X11 support enabled.

### **Nota**

Just enabling ***DISTRO\_FEATURES*** alone doesn't enable feature support for packages. Mechanisms such as making ***PACKAGECONFIG*** track ***DISTRO\_FEATURES*** are used to enable/disable package features.

Two more examples are Bluetooth and NFS support. For a more complete list of features that ships with the Yocto Project and that you can provide with this variable, see the "***Distro Features***" section.

## ***DISTRO\_FEATURES\_DEFAULTS***

Specifies a space-separated list of default distro features provided by the ***OpenEmbedded Build System***. This list should not be modified directly, but instead ***DISTRO\_FEATURES\_OPTED\_OUT*** should be used to prevent default distro features from being enabled.

See ***Default Features*** for more information.

## ***DISTRO\_FEATURES\_FILTER\_NATIVE***

Specifies a list of features that if present in the target ***DISTRO\_FEATURES*** value should be included in ***DISTRO\_FEATURES*** when building native recipes. This variable is used in addition to the features filtered using the ***DISTRO\_FEATURES\_NATIVE*** variable.

## ***DISTRO\_FEATURES\_FILTER\_NATIVESDK***

Specifies a list of features that if present in the target ***DISTRO\_FEATURES*** value should be included in ***DISTRO\_FEATURES*** when building ***nativesdk*** recipes. This variable is used in addition to the features filtered using the ***DISTRO\_FEATURES\_NATIVESDK*** variable.

## ***DISTRO\_FEATURES\_NATIVE***

Specifies a list of features that should be included in ***DISTRO\_FEATURES*** when building native recipes. This variable is used in addition to the features filtered using the ***DISTRO\_FEATURES\_FILTER\_NATIVE*** variable.

## ***DISTRO\_FEATURES\_NATIVESDK***

Specifies a list of features that should be included in ***DISTRO\_FEATURES*** when building ***nativesdk*** recipes. This variable is used in addition to the features filtered using the ***DISTRO\_FEATURES\_FILTER\_NATIVESDK*** variable.

## ***DISTRO\_FEATURES\_OPTED\_OUT***

Specifies a space-separated list of distro features to opt out from when they are provided by the ***DISTRO\_FEATURES\_DEFAULTS*** variable.

You can also opt out of all default features by setting ***DISTRO\_FEATURES\_OPTED\_OUT*** to \*:



```
DISTRO_FEATURES_OPTED_OUT = "*" "
```

See *Default Features* for more information.

### ***DISTRO\_NAME***

The long name of the distribution. For information on the short name of the distribution, see the *DISTRO* variable.

The *DISTRO\_NAME* variable corresponds to a distribution configuration file whose root name is the same as the variable's argument and whose filename extension is `.conf`. For example, the distribution configuration file for the Poky distribution is named `poky.conf` and resides in the `meta-poky/conf/distro` directory of `meta-poky`.

Within that `poky.conf` file, the *DISTRO\_NAME* variable is set as follows:

```
DISTRO_NAME = "Poky (Yocto Project Reference Distro) "
```

Distribution configuration files are located in a `conf/distro` directory within the *Metadata* that contains the distribution configuration.

#### ***Nota***

If the *DISTRO\_NAME* variable is blank, a set of default configurations are used, which are specified within `meta/conf/distro/defaultsetup.conf` also in *OpenEmbedded-Core (OE-Core)*.

### ***DISTRO\_VERSION***

The version of the distribution.

### ***DISTROOVERRIDES***

A colon-separated list of overrides specific to the current distribution. By default, this list includes the value of *DISTRO*.

You can extend *DISTROOVERRIDES* to add extra overrides that should apply to the distribution.

The underlying mechanism behind *DISTROOVERRIDES* is simply that it is included in the default value of *OVERRIDES*.

Here is an example from `meta-poky/conf/distro/poky-tiny.conf`:

```
DISTROOVERRIDES = "poky:poky-tiny"
```

### ***DL\_DIR***

The central download directory used by the build process to store downloads. By default, *DL\_DIR* gets files suitable for mirroring for everything except Git repositories. If you want tarballs of Git repositories, use the *BB\_GENERATE\_MIRROR\_TARBALLS* variable.

You can set this directory by defining the *DL\_DIR* variable in the `build/conf/local.conf` file. This directory is self-maintaining and you should not have to touch it. By default, the directory is `downloads` in the *Build Directory*:

```
#DL_DIR ?= "${TOPDIR}/downloads"
```

To specify a different download directory, simply remove the comment from the line and provide your directory.

During a first build, the system downloads many different source code tarballs from various upstream projects. Downloading can take a while, particularly if your network connection is slow. Tarballs are all stored in the directory defined by *DL\_DIR* and the build system looks there first to find source tarballs.

#### Nota

When wiping and rebuilding, you can preserve this directory to speed up this part of subsequent builds.

You can safely share this directory between multiple builds on the same development machine. For additional information on how the build process gets source files when working behind a firewall or proxy server, see this specific question in the "[FAQ](#)" chapter. You can also refer to the "[Working Behind a Network Proxy](#)" Wiki page.

### *DOC\_COMPRESS*

When inheriting the *compress\_doc* class, this variable sets the compression policy used when the OpenEmbedded build system compresses manual and info pages. By default, the compression method used is *gz* (*gzip*). Other policies available are *xz* and *bz2*.

For information on policies and on how to use this variable, see the comments in the `meta/classes-recipe/compress_doc.bbclass` file.

### *DT\_FILES*

Space-separated list of device tree source files to compile using a recipe that inherits the *devicetree* class. These are relative to the *DT\_FILES\_PATH*.

For convenience, both `.dts` and `.dtb` extensions can be used.

Use an empty string (default) to build all device tree sources within the *DT\_FILES\_PATH* directory.

### *DT\_FILES\_PATH*

When compiling out-of-tree device tree sources using a recipe that inherits the *devicetree* class, this variable specifies the path to the directory containing dts files to build.

Defaults to the *S* directory.

### *DT\_PADDING\_SIZE*

When inheriting the *devicetree* class, this variable specifies the size of padding appended to the device tree blob, used as extra space typically for additional properties during boot.

### *EFI\_ARCH*

The CPU architecture name within EFI standard. Set in `meta/conf/image-uefi.conf`.

### *EFI\_PROVIDER*

When building bootable images (i.e. where `hddimg`, `iso`, or `wic.vmdk` is in *IMAGE\_FSTYPES*), the *EFI\_PROVIDER* variable specifies the EFI bootloader to use. The default is "grub-efi", but "systemd-boot" can be used instead.

See the *systemd-boot* and *image-live* classes for more information.

#### ***EFI\_UKI\_DIR***

The primary place for the UKI image inside the EFI System Partition.

#### ***EFI\_UKI\_PATH***

The path for the UKI image inside the root filesystem.

#### ***ENABLE\_BINARY\_LOCALE\_GENERATION***

Variable that controls which locales for `glibc` are generated during the build (useful if the target device has 64Mbytes of RAM or less).

#### ***ERR\_REPORT\_DIR***

When used with the *report-error* class, specifies the path used for storing the debug files created by the *error reporting tool*, which allows you to submit build errors you encounter to a central database. By default, the value of this variable is `${LOG_DIR}/error-report`.

You can set *ERR\_REPORT\_DIR* to the path you want the error reporting tool to store the debug files as follows in a *configuration file*:

```
ERR_REPORT_DIR = "path"
```

#### ***ERROR\_QA***

Specifies the quality assurance checks whose failures are reported as errors by the OpenEmbedded build system. You set this variable in your distribution configuration file. For a list of the checks you can control with this variable, see the *"insane"* section.

#### ***ESDK\_CLASS\_INHERIT\_DISABLE***

A list of classes to remove from the *INHERIT* value globally within the extensible SDK configuration. The *populate-sdk-ext* class sets the default value:

```
ESDK_CLASS_INHERIT_DISABLE ?= "buildhistory"
```

Some classes are not generally applicable within the extensible SDK context. You can use this variable to disable those classes.

For additional information on how to customize the extensible SDK's configuration, see the *"Configuring the Extensible SDK"* section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

#### ***ESDK\_LOCALCONF\_ALLOW***

A list of variables allowed through from the OpenEmbedded build system configuration into the extensible SDK configuration. By default, the list of variables is empty and is set in the *populate-sdk-ext* class.

This list overrides the variables specified using the *ESDK\_LOCALCONF\_REMOVE* variable as well as other variables automatically added due to the `/` character being found at the start of the value, which is usually indicative of being a path and thus might not be valid on the system where the SDK is installed.

For additional information on how to customize the extensible SDK's configuration, see the *"Configuring the Extensible SDK"* section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### *ESDK\_LOCALCONF\_REMOVE*

A list of variables not allowed through from the OpenEmbedded build system configuration into the extensible SDK configuration. Usually, these are variables that are specific to the machine on which the build system is running and thus would be potentially problematic within the extensible SDK.

By default, *ESDK\_LOCALCONF\_REMOVE* is set in the *populate-sdk-ext* class and excludes the following variables:

- *CONF\_VERSION*
- *BB\_NUMBER\_THREADS*
- *BB\_NUMBER\_PARSE\_THREADS*
- *PARALLEL\_MAKE*
- *PRSERV\_HOST*
- *SSTATE\_MIRRORS DL\_DIR*
- *SSTATE\_DIR TMPDIR*
- *BB\_SERVER\_TIMEOUT*

For additional information on how to customize the extensible SDK's configuration, see the "*Configuring the Extensible SDK*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### *EXCLUDE\_FROM\_SHLIBS*

Triggers the OpenEmbedded build system's shared libraries resolver to exclude an entire package when scanning for shared libraries.

#### Nota

The shared libraries resolver's functionality results in part from the internal function `package_do_shlibs`, which is part of the *do\_package* task. You should be aware that the shared libraries resolver might implicitly define some dependencies between packages.

The *EXCLUDE\_FROM\_SHLIBS* variable is similar to the *PRIVATE\_LIBS* variable, which excludes a package's particular libraries only and not the whole package.

Use the *EXCLUDE\_FROM\_SHLIBS* variable by setting it to "1" for a particular package:

```
EXCLUDE_FROM_SHLIBS = "1"
```

### *EXCLUDE\_FROM\_WORLD*

Directs BitBake to exclude a recipe from world builds (i.e. `bitbake world`). During world builds, BitBake locates, parses and builds all recipes found in every layer exposed in the *build/conf/bblayers.conf* configuration file.

To exclude a recipe from a world build using this variable, set the variable to "1" in the recipe.

**i Nota**

Recipes added to *EXCLUDE\_FROM\_WORLD* may still be built during a world build in order to satisfy dependencies of other recipes. Adding a recipe to *EXCLUDE\_FROM\_WORLD* only ensures that the recipe is not explicitly added to the list of build targets in a world build.

**EXTENDPE**

Used with file and pathnames to create a prefix for a recipe's version based on the recipe's *PE* value. If *PE* is set and greater than zero for a recipe, *EXTENDPE* becomes that value (e.g if *PE* is equal to "1" then *EXTENDPE* becomes "1"). If a recipe's *PE* is not set (the default) or is equal to zero, *EXTENDPE* becomes "".

See the *STAMP* variable for an example.

**EXTENDPKGVS**

The full package version specification as it appears on the final packages produced by a recipe. The variable's value is normally used to fix a runtime dependency to the exact same version of another package in the same recipe:

```
RDEPENDS:${PN}-additional-module = "${PN} (= ${EXTENDPKGVS}) "
```

The dependency relationships are intended to force the package manager to upgrade these types of packages in lock-step.

**EXTERNAL\_KERNEL\_DEVICETREE**

When inheriting *kernel-fit-image* and a *PREFERRED\_PROVIDER* for *virtual/dtb* set to *devicetree*, the variable *EXTERNAL\_KERNEL\_DEVICETREE* can be used to specify a directory containing one or more compiled device tree or device tree overlays to use.

**EXTERNAL\_KERNEL\_TOOLS**

When set, the *EXTERNAL\_KERNEL\_TOOLS* variable indicates that these tools are not in the source tree.

When kernel tools are available in the tree, they are preferred over any externally installed tools. Setting the *EXTERNAL\_KERNEL\_TOOLS* variable tells the OpenEmbedded build system to prefer the installed external tools. See the *kernel-yocto* class in *meta/classes-recipe* to see how the variable is used.

**EXTERNAL\_TOOLCHAIN**

When you intend to use an *external toolchain*, this variable allows to specify the directory where this toolchain was installed.

**EXTERNALSRC**

When inheriting the *externalsrc* class, this variable points to the source tree, which is outside of the OpenEmbedded build system. When set, this variable sets the *S* variable, which is what the OpenEmbedded build system uses to locate unpacked recipe source code.

See the "*externalsrc*" section for details. You can also find information on how to use this variable in the "*Building Software from an External Source*" section in the Yocto Project Development Tasks Manual.

**EXTERNALSRC\_BUILD**

When inheriting the *externalsrc* class, this variable points to the directory in which the recipe's source code is

built, which is outside of the OpenEmbedded build system. When set, this variable sets the *B* variable, which is what the OpenEmbedded build system uses to locate the *Build Directory*.

See the "*externalsrc*" section for details. You can also find information on how to use this variable in the "*Building Software from an External Source*" section in the Yocto Project Development Tasks Manual.

### *EXTRA\_AUTORECONF*

For recipes inheriting the *autotools\** class, you can use *EXTRA\_AUTORECONF* to specify extra options to pass to the *autoreconf* command that is executed during the *do\_configure* task.

The default value is "--exclude=autopoint".

### *EXTRA\_IMAGE\_FEATURES*

A list of additional features to include in an image. When listing more than one feature, separate them with a space.

Typically, you configure this variable in your *build/conf/local.conf* file for local modifications, or in your distro *configuration file* for permanent changes. Although you can use this variable from within a recipe, best practices dictate that you do not.

#### **Nota**

To enable primary features from within the image recipe, use the *IMAGE\_FEATURES* variable.

Here are some examples of features you can add:

- "dbg-pkgs" --- adds -dbg packages for all installed packages including symbol information for debugging and profiling.
- "empty-root-password" --- This feature can be used if you want to allow root login with an empty password.
- "allow-empty-password" --- Allows Dropbear and OpenSSH to accept logins from accounts having an empty password string.
- "allow-root-login" --- Allows Dropbear and OpenSSH to accept root logins.
- "post-install-logging" --- Enables logging postinstall script runs to the */var/log/postinstall.log* file on first boot of the image on the target system.
- "dev-pkgs" --- adds -dev packages for all installed packages. This is useful if you want to develop against the libraries in the image.
- "read-only-rootfs" --- creates an image whose root filesystem is read-only. See the "*Creazione di un Filesystem Root di Sola Lettura*" section in the Yocto Project Security Manual for more information
- "tools-debug" --- adds debugging tools such as gdb and strace.
- "tools-sdk" --- adds development tools such as gcc, make, pkgconfig and so forth.
- "tools-testapps" --- adds useful testing tools such as ts\_print, aplay, arecord and so forth.

For a complete list of image features that ships with the Yocto Project, see the "*Image Features*" section.

For an example that shows how to customize your image by using this variable, see the "[Customizing Images Using Custom `IMAGE\_FEATURES` and `EXTRA\_IMAGE\_FEATURES`](#)" section in the Yocto Project Development Tasks Manual.

### **`EXTRA_IMAGECMD`**

Specifies additional options for the image creation command that has been specified in `IMAGE_CMD`. When setting this variable, use an override for the associated image type. Here is an example:

```
EXTRA_IMAGECMD:ext3 ?= "-i 4096"
```

### **`EXTRA_IMAGEDEPENDS`**

A list of recipes to build that do not provide packages for installing into the root filesystem.

Sometimes a recipe is required to build the final image but is not needed in the root filesystem. You can use the `EXTRA_IMAGEDEPENDS` variable to list these recipes and thus specify the dependencies. A typical example is a required bootloader in a machine configuration.

#### **Nota**

To add packages to the root filesystem, see the various `RDEPENDS` and `RRECOMMENDS` variables.

### **`EXTRA_OECMAKE`**

Additional `CMake` options. See the `cmake` class for additional information.

### **`EXTRA_OECONF`**

Additional `configure` script options. See `PACKAGECONFIG_CONFARGS` for additional information on passing configure script options.

### **`EXTRA_OEMAKE`**

Additional GNU `make` options.

Because the `EXTRA_OEMAKE` defaults to "", you need to set the variable to specify any required GNU options.

`PARALLEL_MAKE` and `PARALLEL_MAKEINST` also make use of `EXTRA_OEMAKE` to pass the required flags.

### **`EXTRA_OEMESON`**

Additional `Meson` options. See the `meson` class for additional information.

In addition to standard Meson options, such options correspond to `Meson build options` defined in the `meson_options.txt` file in the sources to build. Here is an example:

```
EXTRA_OEMESON = "-Dpython=disabled -Dvalgrind=disabled"
```

Note that any custom value for the Meson `--buildtype` option should be set through the `MESON_BUILDTYPE` variable.

### **`EXTRA_OESCONS`**

When inheriting the `scons` class, this variable specifies additional configuration options you want to pass to the `scons` command line.

### EXTRA\_USERS\_PARAMS

When inheriting the *extrausers* class, this variable provides image level user and group operations. This is a more global method of providing user and group configuration as compared to using the *useradd\** class, which ties user and group configurations to a specific recipe.

The set list of commands you can configure using the *EXTRA\_USERS\_PARAMS* is shown in the *extrausers* class. These commands map to the normal Unix commands of the same names:

```
# EXTRA_USERS_PARAMS = "\
# useradd -p '' tester; \
# groupadd developers; \
# userdel nobody; \
# groupdel -g video; \
# groupmod -g 1020 developers; \
# usermod -s /bin/sh tester; \
# "
```

Hardcoded passwords are supported via the *-p* parameters for *useradd* or *usermod*, but only hashed.

Here is an example that adds two users named "tester-jim" and "tester-sue" and assigns passwords. First on host, create the (escaped) password hash:

```
printf "%q" $(mkpasswd -m sha256crypt tester01)
```

The resulting hash is set to a variable and used in *useradd* command parameters:

```
inherit extrausers
PASSWD = "\$X\$ABC123\$A-Long-Hash"
EXTRA_USERS_PARAMS = "\
    useradd -p '${PASSWD}' tester-jim; \
    useradd -p '${PASSWD}' tester-sue; \
    "
```

Finally, here is an example that sets the root password:

```
inherit extrausers
EXTRA_USERS_PARAMS = "\
    usermod -p '${PASSWD}' root; \
    "
```

#### Nota

From a security perspective, hardcoding a default password is not generally a good idea or even legal in some jurisdictions. It is recommended that you do not do this if you are building a production image.

Additionally there is a special *passwd-expire* command that will cause the password for a user to be expired and thus force changing it on first login, for example:



```
EXTRA_USERS_PARAMS += " useradd myuser; passwd-expire myuser; "
```

#### **Nota**

At present, `passwd-expire` may only work for remote logins when using OpenSSH and not dropbear as an SSH server.

### ***EXTRANATIVEPATH***

A list of subdirectories of `${STAGING_BINDIR_NATIVE}` added to the beginning of the environment variable `PATH`. As an example, the following prepends `"${STAGING_BINDIR_NATIVE}/foo:${STAGING_BINDIR_NATIVE}/bar:"` to `PATH`:

```
EXTRANATIVEPATH = "foo bar"
```

### ***FAKEROOT***

See [FAKEROOT](#) in the BitBake manual.

### ***FAKEROOTBASEENV***

See [FAKEROOTBASEENV](#) in the BitBake manual.

### ***FAKEROOTCMD***

See [FAKEROOTCMD](#) in the BitBake manual.

### ***FAKEROOTDIRS***

See [FAKEROOTDIRS](#) in the BitBake manual.

### ***FAKEROOTENV***

See [FAKEROOTENV](#) in the BitBake manual.

### ***FAKEROOTNOENV***

See [FAKEROOTNOENV](#) in the BitBake manual.

### ***FC***

The minimal command and arguments used to run the Fortran compiler.

### ***FEATURE\_PACKAGES***

Defines one or more packages to include in an image when a specific item is included in [IMAGE\\_FEATURES](#). When setting the value, [FEATURE\\_PACKAGES](#) should have the name of the feature item as an override. Here is an example:

```
FEATURE_PACKAGES_widget = "package1 package2"
```

In this example, if "widget" were added to [IMAGE\\_FEATURES](#), package1 and package2 would be included in the image.

#### **Nota**

Packages installed by features defined through `FEATURE_PACKAGES` are often package groups. While similarly named, you should not confuse the `FEATURE_PACKAGES` variable with package groups, which are discussed elsewhere in the documentation.

### `FEED_DEPLOYDIR_BASE_URI`

Points to the base URL of the server and location within the document-root that provides the metadata and packages required by OPKG to support runtime package management of IPK packages. You set this variable in a *configuration file*.

Consider the following example:

```
FEED_DEPLOYDIR_BASE_URI = "http://192.168.7.1/BOARD-dir"
```

This example assumes you are serving your packages over HTTP and your databases are located in a directory named `BOARD-dir`, which is underneath your HTTP server's document-root. In this case, the OpenEmbedded build system generates a set of configuration files for you in your target that work with the feed.

### `FETCHCMD`

See `FETCHCMD` in the BitBake manual.

### `FILE`

See `FILE` in the BitBake manual.

### `FILES`

The list of files and directories that are placed in a package. The `PACKAGES` variable lists the packages generated by a recipe.

To use the `FILES` variable, provide a package name override that identifies the resulting package. Then, provide a space-separated list of files or paths that identify the files you want included as part of the resulting package. Here is an example:

```
FILES:${PN} += "${bindir}/mydir1 ${bindir}/mydir2/myfile"
```

#### Nota

- When specifying files or paths, you can pattern match using Python's `glob` syntax. For details on the syntax, see the documentation by following the previous link.
- When specifying paths as part of the `FILES` variable, it is good practice to use appropriate path variables. For example, use `${sysconfdir}` rather than `/etc`, or `${bindir}` rather than `/usr/bin`. You can find a list of these variables at the top of the `meta/conf/bitbake.conf` file in *OpenEmbedded-Core (OE-Core)*. You will also find the default values of the various `FILES:*` variables in this file.

If some of the files you provide with the `FILES` variable are editable and you know they should not be overwritten during the package update process by the Package Management System (PMS), you can identify these files so that the PMS will not overwrite them. See the `CONFFILES` variable for information on how to identify these files to the PMS.

### *FILES\_SOLIBSDEV*

Defines the file specification to match *SOLIBSDEV*. In other words, *FILES\_SOLIBSDEV* defines the full path name of the development symbolic link (symlink) for shared libraries on the target platform.

The following statement from the `bitbake.conf` shows how it is set:

```
FILES_SOLIBSDEV ?= "${base_libdir}/lib*${SOLIBSDEV} ${libdir}/lib*${SOLIBSDEV}"
```

### *FILESEXTRAPATHS*

A colon-separated list to extend the search path the OpenEmbedded build system uses when looking for files and patches as it processes recipes and append files. The default directories BitBake uses when it processes recipes are initially defined by the *FILESPATH* variable. You can extend *FILESPATH* variable by using *FILESEXTRAPATHS*.

Best practices dictate that you accomplish this by using *FILESEXTRAPATHS* from within a `.bbappend` file and that you prepend paths as follows:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"
```

In the above example, the build system first looks for files in a directory that has the same name as the corresponding append file.

#### Nota

When extending *FILESEXTRAPATHS*, be sure to use the immediate expansion (`:=`) operator. Immediate expansion makes sure that BitBake evaluates *THISDIR* at the time the directive is encountered rather than at some later time when expansion might result in a directory that does not contain the files you need.

Also, include the trailing separating colon character if you are prepending. The trailing colon character is necessary because you are directing BitBake to extend the path by prepending directories to the search path.

Here is another common use:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/files:"
```

In this example, the build system extends the *FILESPATH* variable to include a directory named `files` that is in the same directory as the corresponding append file.

This next example specifically adds three paths:

```
FILESEXTRAPATHS:prepend := "path_1:path_2:path_3:"
```

A final example shows how you can extend the search path and include a *MACHINE*-specific override, which is useful in a BSP layer:

```
FILESEXTRAPATHS:prepend:intel-x86-common := "${THISDIR}/${PN}:"
```

The previous statement appears in the `linux-yocto-dev.bbappend` file, which is found in the *I Repository del Codice Sorgente di Yocto Project* in `meta-intel/common/recipes-kernel/linux`. Here, the machine override is a special `PACKAGE_ARCH` definition for multiple `meta-intel` machines.

#### **i** Nota

For a layer that supports a single BSP, the override could just be the value of `MACHINE`.

By prepending paths in `.bbappend` files, you allow multiple append files that reside in different layers but are used for the same recipe to correctly extend the path.

### FILESOVERRIDES

A colon-separated list to specify a subset of `OVERRIDES` used by the OpenEmbedded build system for creating `FILESPATH`. The `FILESOVERRIDES` variable uses overrides to automatically extend the `FILESPATH` variable. For an example of how that works, see the `FILESPATH` variable description. Additionally, you find more information on how overrides are handled in the "Conditional Syntax (Overrides)" section of the BitBake User Manual.

By default, the `FILESOVERRIDES` variable is defined as:

```
FILESOVERRIDES = "${TRANSLATED_TARGET_ARCH}:${MACHINEOVERRIDES}:$
↳ {DISTROOVERRIDES}"
```

#### **i** Nota

Do not hand-edit the `FILESOVERRIDES` variable. The values match up with expected overrides and are used in an expected manner by the build system.

### FILESPATH

A colon-separated list specifying the default set of directories the OpenEmbedded build system uses when searching for patches and files.

During the build process, BitBake searches each directory in `FILESPATH` in the specified order when looking for files and patches specified by each `file:// URI` in a recipe's `SRC_URI` statements.

The default value for the `FILESPATH` variable is defined in the `base` class found in `meta/classes-global` in *OpenEmbedded-Core (OE-Core)*:

```
FILESPATH = "${@oe.utils.base_set_filespath(["${FILE_DIRNAME}/${BP}", \
"${FILE_DIRNAME}/${BPN}", "${FILE_DIRNAME}/files"], d)}
```

The `FILESPATH` variable is automatically extended using the overrides from the `FILESOVERRIDES` variable.

#### **i** Nota

- Do not hand-edit the `FILESPATH` variable. If you want the build system to look in directories other than the defaults, extend the `FILESPATH` variable by using the `FILESEXPATHTS` variable.

- Be aware that the default *FILESPATH* directories do not map to directories in custom layers where append files (*.bbappend*) are used. If you want the build system to find patches or files that reside with your append files, you need to extend the *FILESPATH* variable by using the *FILESEXTRAPATHS* variable.

You can take advantage of this searching behavior in useful ways. For example, consider a case where there is the following directory structure for general and machine-specific configurations:

```
files/defconfig
files/MACHINEA/defconfig
files/MACHINEB/defconfig
```

Also in the example, the *SRC\_URI* statement contains "*file://defconfig*". Given this scenario, you can set *MACHINE* to "MACHINEA" and cause the build system to use files from *files/MACHINEA*. Set *MACHINE* to "MACHINEB" and the build system uses files from *files/MACHINEB*. Finally, for any machine other than "MACHINEA" and "MACHINEB", the build system uses files from *files/defconfig*.

You can find out more about the patching process in the "*Applicazione delle Patch*" section in the Yocto Project Overview and Concepts Manual and the "*Patching Code*" section in the Yocto Project Development Tasks Manual. See the *do\_patch* task as well.

### *FILESYSTEM\_PERMS\_TABLES*

Allows you to define your own file permissions settings tables as part of your configuration for the packaging process. For example, suppose you need a consistent set of custom permissions for a set of groups and users across an entire work project. It is best to do this in the packages themselves but this is not always possible.

By default, the OpenEmbedded build system uses the *fs-perms.txt*, *fs-perms-volatile-log.txt* and *fs-perms-volatile-tmp.txt* which are located in the *meta/files* folder in *OpenEmbedded-Core (OE-Core)*. If you create your own permission setting table files, you should place those in your layer.

You can override the value of *FILESYSTEM\_PERMS\_TABLES* variable in your distribution configuration file to point to your custom permission table files. You can specify one or more file permissions setting tables. The paths that you specify to these files must be defined within the *BBPATH* variable.

In order to disable the volatile log, which is enabled by default, one can remove the *files/fs-perms-volatile-log.txt* value from *FILESYSTEM\_PERMS\_TABLES*. Similarly, in order to disable the volatile tmp, one can remove the *files/fs-perms-volatile-tmp.txt* value.

For guidance on how to define your own file permissions settings tables, examine the existing *fs-perms.txt*, *fs-perms-volatile-log.txt* and *fs-perms-volatile-tmp.txt* files.

### *FIRMWARE\_COMPRESSION*

The *FIRMWARE\_COMPRESSION* allows compressing the firmware provided by the *linux-firmware* recipe. The default value of this variable is an empty string (no compression), and the possible values it can take are *xz* and *zst*. This can allow significant disk space savings.

For this to work, the Linux Kernel requires the *CONFIG\_FW\_LOADER\_COMPRESS\_XZ* or *CONFIG\_FW\_LOADER\_COMPRESS\_ZSTD* configuration options to be set.

### *FIT\_ADDRESS\_CELLS*

Specifies the value of the `#address-cells` value for the description of the FIT image.

The default value is set to "1" by the *kernel-fit-image* class, which corresponds to 32 bit addresses.

For platforms that need to set 64 bit addresses, for example in *UBOOT\_LOADADDRESS* and *UBOOT\_ENTRYPOINT*, you need to set this value to "2", as two 32 bit values (cells) will be needed to represent such addresses.

Here is an example setting "0x400000000" as a load address:

```
FIT_ADDRESS_CELLS = "2"
UBOOT_LOADADDRESS = "0x04 0x00000000"
```

See [more details about #address-cells](#).

### *FIT\_CONF\_DEFAULT\_DTB*

Specifies the default device tree binary (dtb) file for a FIT image when multiple ones are provided.

This variable is used in the *kernel-fit-image* class.

### *FIT\_CONF\_MAPPINGS*

When inheriting the *kernel-fit-image*, the *FIT\_CONF\_MAPPINGS* variable allows specifying mappings to rename configuration nodes or add extra configuration nodes for existing device tree blobs (DTBs) in FIT images. This provides flexibility when a 1 to 1 mapping between DTB names and configuration node names does not work, such as when the kernel defines a kernel specific name but the bootloader uses a different name. This might be the case when maintaining compatibility with existing boot scripts or bootloader configurations. But there are other use cases as well.

The variable accepts a space-separated list of mapping commands:

- `dtb-conf:DTB_NAME:NEW_NAME` Renames the configuration node for a specific DTB. The `DTB_NAME` is the name of the DTB without its `.dtb` suffix.
- `dtb-extra-conf:DTB_NAME:EXTRA_NAME` Creates an additional configuration node for an existing DTB. This is useful when you need to provide alternative names for the same hardware configuration to maintain compatibility with existing boot scripts or bootloader configurations or just need an alias configuration name for some other reason.

Per esempio:

```
FIT_CONF_MAPPINGS = "\
    dtb-extra-conf:am335x-bonegreen:bonegreen \
    dtb-conf:am335x-boneblack:bbblack"
```

This generates three configuration nodes from two DTBs:

- `am335x-bonegreen`: the original configuration node for the `am335x-bonegreen` device tree
- `bonegreen`: an extra configuration node for the same `am335x-bonegreen` DTB
- `bbblack`: a renamed configuration node for the `am335x-boneblack` DTB

The *kernel-fit-image* class validates all mappings and ensures they match existing DTBs.

### ***FIT\_CONF\_PREFIX***

When using the *kernel-fit-image*, this is the prefix used for creating FIT configuration nodes. Its default value is "conf-".

### ***FIT\_DESC***

Specifies the description string encoded into a FIT image. The default value is set by the *kernel-fit-image* class as follows:

```
FIT_DESC ?= "U-Boot fitImage for ${DISTRO_NAME}/${PV}/${MACHINE}"
```

### ***FIT\_GENERATE\_KEYS***

Decides whether to generate the keys for signing the FIT image if they don't already exist. The keys are created in *UBOOT\_SIGN\_KEYDIR*. The default value is set to "0" by the *kernel-fit-image* class.

### ***FIT\_HASH\_ALG***

Specifies the hash algorithm used in creating the FIT Image. This variable is set by default to "sha256" by the *kernel-fit-image* class.

### ***FIT\_KERNEL\_COMP\_ALG***

The compression algorithm to use for the kernel image inside the FIT Image. At present, the only supported values are "gzip" (default), "lzo" or "none".

This variable is used in the *kernel-uboot* class.

### ***FIT\_KERNEL\_SIGN\_ENABLE***

This variable is used by the *kernel-fit-image* class to enable or disable signing of the FIT image. The default value of *FIT\_KERNEL\_SIGN\_ENABLE* is the value of *UBOOT\_SIGN\_ENABLE*, which means that when U-Boot FIT image signing is enabled, the FIT image will also be signed at build-time and U-Boot will verify the FIT image signature at run-time.

If this variable is set to "1", the FIT image will be signed using the key specified by *FIT\_KERNEL\_SIGN\_KEYNAME* from the directory *FIT\_KERNEL\_SIGN\_KEYDIR*.

If this variable is overridden, the *FIT\_KERNEL\_SIGN\_KEYDIR* and *FIT\_KERNEL\_SIGN\_KEYNAME* variables should also be set appropriately.

### ***FIT\_KERNEL\_SIGN\_KEYDIR***

This variable is used by the *kernel-fit-image* class. The default value of *FIT\_KERNEL\_SIGN\_KEYDIR* is the value of *UBOOT\_SIGN\_KEYDIR*, which means the kernel is signed at build-time with a private key found in *UBOOT\_SIGN\_KEYDIR* and U-Boot gets the public key from the same directory injected into its DTB for the on-target verification of the FIT image.

If this variable is overridden, the *FIT\_KERNEL\_SIGN\_ENABLE* and *FIT\_KERNEL\_SIGN\_KEYNAME* variables should also be set appropriately.

### ***FIT\_KERNEL\_SIGN\_KEYNAME***

This variable is used by the *kernel-fit-image* class. The default value of *FIT\_KERNEL\_SIGN\_KEYNAME* is the value of *UBOOT\_SIGN\_KEYNAME*, which means the kernel is signed at build-time with a private key named according to *UBOOT\_SIGN\_KEYNAME* and U-Boot gets the public key with the same name injected into its DTB for on-target verification of the FIT image.

If this variable is overridden, the `FIT_KERNEL_SIGN_ENABLE` and `FIT_KERNEL_SIGN_KEYDIR` variables should also be set appropriately.

#### `FIT_KEY_GENRSA_ARGS`

Arguments to `openssl genrsa` for generating a RSA private key for signing the FIT image. The default value is set to "-F4" by the `kernel-fit-image` class.

#### `FIT_KEY_REQ_ARGS`

Arguments to `openssl req` for generating a certificate for signing the FIT image. The default value is "-batch -new" by the `kernel-fit-image` class, "batch" for non interactive mode and "new" for generating new keys.

#### `FIT_KEY_SIGN_PKCS`

Format for the public key certificate used for signing the FIT image. The default value is set to "x509" by the `kernel-fit-image` class.

#### `FIT_LOADABLE_ARCH`

Architecture the loadables defined in `FIT_LOADABLES`; the value will be used for the `arch` property of the loadable. If no value is defined for a specific loadable, the kernel architecture will be used.

This variable cannot be used directly, but only defining flags on it.

Example:

```
FIT_LOADABLES = "foo"
FIT_LOADABLE_ARCH[foo] = "arm"
```

#### `FIT_LOADABLE_COMPRESSION`

Compression type for the loadables defined in `FIT_LOADABLES`; the value will be used for the `compression` property of the loadable. If no value is defined for a specific loadable, its `compression` property will be set to `none`.

This variable cannot be used directly, but only defining flags on it.

Example:

```
FIT_LOADABLES = "foo"
FIT_LOADABLE_COMPRESSION[foo] = "gzip"
```

#### Nota

The binary should already be compressed, as no compression is performed by the `kernel-fit-image` class.

#### `FIT_LOADABLE_DESCRIPTION`

Description for the loadables defined in `FIT_LOADABLES`; the value will be used for the `description` property of the loadable. If no value is defined for a specific loadable, its description will be set to the loadable name followed by a space plus the string `loadable`.

This variable cannot be used directly, but only defining flags on it.

Example:



```
FIT_LOADABLES = "foo"
FIT_LOADABLE_DESCRIPTION[foo] = "Foo firmware binary"
```

### ***FIT\_LOADABLE\_ENTRYPOINT***

Entry point for the loadables defined in *FIT\_LOADABLES*; the value will be used for the `entry` property of the loadable. If no value is defined for a specific loadable, the `entry` property will be omitted.

This variable cannot be used directly, but only defining flags on it.

Example:

```
FIT_LOADABLES = "foo"
FIT_LOADABLE_ENTRYPOINT[foo] = "0x80234000"
```

### ***FIT\_LOADABLE\_FILENAME***

Filename (or relative path) for the loadables defined in *FIT\_LOADABLES*; this will be used to search for the binary to include and is therefore mandatory for each loadable. Binary files to be included need to be located in *DEPLOY\_DIR\_IMAGE*.

This variable cannot be used directly, but only defining flags on it.

Example:

```
FIT_LOADABLES = "foo"
FIT_LOADABLE_FILENAME[foo] = "foo-firmware.bin"
```

### ***FIT\_LOADABLE\_LOADADDRESS***

Load address for the loadables defined in *FIT\_LOADABLES*; the value will be used for the `load` property of the loadable. This is mandatory for each loadable.

This variable cannot be used directly, but only defining flags on it.

Example:

```
FIT_LOADABLES = "foo"
FIT_LOADABLE_LOADADDRESS[foo] = "0x80230000"
```

### ***FIT\_LOADABLE\_OS***

Operating system for the loadables defined in *FIT\_LOADABLES*; the value will be used for the `os` property of the loadable. If no value is defined for a specific loadable, the `os` property will be set to `linux`.

This variable cannot be used directly, but only defining flags on it.

Example:

```
FIT_LOADABLES = "foo"
FIT_LOADABLE_OS[foo] = "linux"
```

### ***FIT\_LOADABLE\_TYPE***

Type for the loadables defined in *FIT\_LOADABLES*; the value will be used for the `type` property of the loadable. If no value is defined for a specific loadable, the `type` property will be set to `firmware`.

This variable cannot be used directly, but only defining flags on it.

Example:

```
FIT_LOADABLES = "foo"
FIT_LOADABLE_TYPE[foo] = "firmware"
```

## ***FIT\_LOADABLES***

Space-separated list of loadables to add to a FIT image in addition to regular ones (kernel, initramfs, dtb etc.). Values specified here will be used as node names inside the FIT image; all of them will be included in all configurations by using the `loadables` property.

For each loadable specified in this variable, additional parameters can be defined using *FIT\_LOADABLE\_ARCH*, *FIT\_LOADABLE\_COMPRESSION*, *FIT\_LOADABLE\_DESCRIPTION*, *FIT\_LOADABLE\_ENTRYPOINT*, *FIT\_LOADABLE\_FILENAME*, *FIT\_LOADABLE\_LOADADDRESS*, *FIT\_LOADABLE\_OS* and *FIT\_LOADABLE\_TYPE*.

This variable is used by the *kernel-fit-image* class and is empty by default.

For example, the following configuration adds as loadables a TF-A BL31 firmware and a (compressed) TEE firmware, to be loaded respectively at 0x204E0000 and 0x96000000:

```
FIT_LOADABLES = "atf tee"

FIT_LOADABLE_FILENAME[atf] = "bl31.bin"
FIT_LOADABLE_DESCRIPTION[atf] = "TF-A Firmware"
FIT_LOADABLE_TYPE[atf] = "tfa-bl31"
FIT_LOADABLE_ARCH[atf] = "arm64"
FIT_LOADABLE_OS[atf] = "arm-trusted-firmware"
FIT_LOADABLE_LOADADDRESS[atf] = "0x204E0000"
FIT_LOADABLE_ENTRYPOINT[atf] = "0x204E0000"

FIT_LOADABLE_FILENAME[tee] = "tee.bin.gz"
FIT_LOADABLE_COMPRESSION[tee] = "gzip"
FIT_LOADABLE_TYPE[tee] = "tee"
FIT_LOADABLE_OS[tee] = "tee"
FIT_LOADABLE_LOADADDRESS[tee] = "0x96000000"
```

and will be converted to the following FIT source:

```
images {
    atf {
        description = "TF-A Firmware";
        type = "tfa-bl31";
        compression = "none";
        data = /incbin/("<DEPLOY_DIR_IMAGE>/bl31.bin");
        arch = "arm64";
        os = "arm-trusted-firmware";
```

(continues on next page)

(continua dalla pagina precedente)

```

        load = <0x204E0000>;
        entry = <0x204E0000>;
    };
    tee {
        description = "tee loadable";
        type = "tee";
        compression = "gzip";
        data = /incbin/("<DEPLOY_DIR_IMAGE>/tee.bin.gz");
        arch = "arm64";
        os = "tee";
        load = <0x96000000>;
    };
};

configurations {
    default = "<my-board>.dtb";
    <my-board>.dtb {
        description = "1 Linux kernel, FDT blob, loadables";
        kernel = "kernel-1";
        fdt = "<my-board>.dtb";
        loadables = "atf", "tee";
    };
};
};

```

### ***FIT\_MKIMAGE\_EXTRA\_OPTS***

When inheriting the *kernel-fit-image*, the *FIT\_MKIMAGE\_EXTRA\_OPTS* variable allows passing extra options to *mkimage* during FIT image generation, providing flexibility for platforms that require additional *mkimage* arguments beyond the defaults.

Per esempio:

```
FIT_MKIMAGE_EXTRA_OPTS = "-B 8 -E"
```

This results in the *mkimage* command being invoked as:

```
mkimage -B 8 -E -f fit-image.its fitImage
```

### ***FIT\_OS***

The *FIT\_OS* variable controls the *os* field of the kernel and various other images in the FIT image. Set to "efi" to load a kernel with EFI stub as an EFI application. The default is "linux".

### ***FIT\_PAD\_ALG***

Specifies the padding algorithm used in creating the FIT Image. The default value is set to "pkcs-1.5" by the *kernel-fit-image* class.

### ***FIT\_SIGN\_ALG***

Specifies the signature algorithm used in creating the FIT Image. This variable is set by default to "rsa2048"

by the *kernel-fit-image* class.

### ***FIT\_SIGN\_INDIVIDUAL***

If set to "1", the *kernel-fit-image* class signs each image node individually, including the kernel, DTB, RAM disk, and any other image types present in the FIT image, in addition to signing the configuration nodes. This can be useful if you need to verify signatures outside of the U-Boot boot process. By default, this variable is set to "0".

If *UBOOT\_SIGN\_ENABLE* is set to "1" and *FIT\_SIGN\_INDIVIDUAL* remains at its default value of "0", only the configuration nodes are signed. Since configuration nodes include hashes of their referenced image nodes, the integrity of the entire FIT image is ensured as long as the image nodes are loaded via the configuration nodes and the hashes of the image nodes are checked. That's usually the case.

Enabling *FIT\_SIGN\_INDIVIDUAL* typically increases complexity for little benefit. There might be exceptions such as image nodes that are not referenced by any configuration node or loaded directly for whatever reason. For most use cases, setting this variable to "0" provides sufficient security.

For further details, refer to the official U-Boot documentation: [U-Boot fit signature](#) and more specifically at: [U-Boot signed configurations](#).

Signing only the image nodes is intentionally not implemented by *OpenEmbedded-Core (OE-Core)*, as it is vulnerable to mix-and-match attacks.

### ***FIT\_SIGN\_NUMBITS***

Size of the private key used in the FIT image, in number of bits. The default value for this variable is set to "2048" by the *kernel-fit-image* class.

### ***FIT\_UBOOT\_ENV***

This variable allows to add a U-Boot script as a text file to the FIT image. Such a script can be sourced from the U-Boot shell.

When inheriting the *kernel-fit-image* class a script file should be included in the *SRC\_URI* of the Linux kernel recipe.

Esempio

- Add a script `boot.cmd` to the Linux kernel recipe:

```
FIT_UBOOT_ENV = "boot.cmd"
SRC_URI += "file://${FIT_UBOOT_ENV}"
```

- Use the script file from the U-Boot shell. The name of the script in FIT image is `bootscr-${FIT_UBOOT_ENV}`. This example loads the FIT image from a TFTP server:

```
tftp $loadaddr $fit_tftp_path
source $loadaddr#bootscr-boot.cmd
```

More information can be found in the official U-Boot documentation: [U-Boot source command](#)

### ***FONT\_EXTRA\_RDEPENDS***

When inheriting the *fontcache* class, this variable specifies the runtime dependencies for font packages. By default, the *FONT\_EXTRA\_RDEPENDS* is set to "fontconfig-utils".

### FONT\_PACKAGES

When inheriting the *fontcache* class, this variable identifies packages containing font files that need to be cached by Fontconfig. By default, the *fontcache* class assumes that fonts are in the recipe's main package (i.e. `${PN}`). Use this variable if fonts you need are in a package other than that main package.

### FORCE\_RO\_REMOVE

Forces the removal of the packages listed in `ROOTFS_RO_UNNEEDED` during the generation of the root filesystem.

Set the variable to "1" to force the removal of these packages.

### FULL\_OPTIMIZATION

The options to pass in *TARGET\_CFLAGS* and *CFLAGS* when compiling an optimized system. This variable defaults to `"-O2 ${DEBUG_LEVELFLAG}"`.

### GCCPIE

Enables Position Independent Executables (PIE) within the GNU C Compiler (GCC). Enabling PIE in the GCC makes Return Oriented Programming (ROP) attacks much more difficult to execute.

By default the `security_flags.inc` file enables PIE by setting the variable as follows:

```
GCCPIE ?= "--enable-default-pie"
```

### GCCVERSION

Specifies the default version of the GNU C Compiler (GCC) used for compilation. By default, *GCCVERSION* is set to "8.x" in the `meta/conf/distro/include/tcmode-default.inc` include file:

```
GCCVERSION ?= "8.%"
```

You can override this value by setting it in a *configuration file* such as a distro configuration file, granted that the recipes associated to this version of GCC exist in your workspace.

### GDB

The minimal command and arguments to run the GNU Debugger.

### GIR\_EXTRA\_LIBS\_PATH

Allows to specify an extra search path for `.so` files in GLib related recipes using GObject introspection, and which do not compile without this setting. See the "*Enabling GObject Introspection Support*" section for details.

### GITDIR

The directory in which a local copy of a Git repository is stored when it is cloned.

### GITHUB\_BASE\_URI

When inheriting the *github-releases* class, specifies the base URL for fetching releases for the github project you wish to fetch sources from. The default value is as follows:

```
GITHUB_BASE_URI ?= "https://github.com/${BPN}/${BPN}/releases/"
```

### GLIBC\_GENERATE\_LOCALES

Specifies the list of GLIBC locales to generate should you not wish to generate all LIBC locals, which can be time consuming.

**i Nota**

If you specifically remove the locale `en_US.UTF-8`, you must set *IMAGE\_LINGUAS* appropriately.

You can set *GLIBC\_GENERATE\_LOCALES* in your *build/conf/local.conf* file for local testing or in your distro *configuration file*.

By default, all locales are generated:

```
GLIBC_GENERATE_LOCALES = "en_GB.UTF-8 en_US.UTF-8"
```

**GO\_IMPORT**

When inheriting the *go* class, this mandatory variable sets the import path for the Go package that will be created for the code to build. If you have a `go.mod` file in the source directory, this typically matches the path in the `module` line in this file.

Other Go programs importing this package will use this path.

Here is an example setting from the *go-helloworld\_0.1.bb* recipe:

```
GO_IMPORT = "golang.org/x/example"
```

**GO\_INSTALL**

When inheriting the *go* class, this optional variable specifies which packages in the sources should be compiled and installed in the Go build space by the *go install* command.

Here is an example setting from the *crucible* recipe:

```
GO_INSTALL = "\
    ${GO_IMPORT}/cmd/crucible \
    ${GO_IMPORT}/cmd/habtool \
"
```

By default, *GO\_INSTALL* is defined as:

```
GO_INSTALL ?= "${GO_IMPORT}/..."
```

The `...` wildcard means that it will catch all packages found in the sources.

See the *GO\_INSTALL\_FILTEROUT* variable for filtering out unwanted packages from the ones found from the *GO\_INSTALL* value.

**GO\_INSTALL\_FILTEROUT**

When using the Go "vendor" mechanism to bring in dependencies for a Go package, the default *GO\_INSTALL* setting, which uses the `...` wildcard, will include the vendored packages in the build, which produces incorrect results.

There are also some Go packages that are structured poorly, so that the `...` wildcard results in building example or test code that should not be included in the build, or could fail to build.

This optional variable allows for filtering out a subset of the sources. It defaults to excluding everything under the `vendor` subdirectory under package's main directory. This is the normal location for vendored packages, but it can be overridden by a recipe to filter out other subdirectories if needed.

### ***GO\_WORKDIR***

When using Go Modules, the current working directory must be the directory containing the `go.mod` file, or one of its subdirectories. When the `go` tool is used, it will automatically look for the `go.mod` file in the Go working directory or in any parent directory, but not in subdirectories.

When using the *go-mod* class to use Go modules, the optional *GO\_WORKDIR* variable, defaulting to the value of *GO\_IMPORT*, allows to specify a different Go working directory.

### ***GROUPADD\_PARAM***

When inheriting the *useradd*\* class, this variable specifies for a package what parameters should be passed to the `groupadd` command if you wish to add a group to the system when the package is installed.

Here is an example from the `dbus` recipe:

```
GROUPADD_PARAM:${PN} = "-r netdev"
```

More than one group can be added by separating each set of different groups' parameters with a semicolon.

Here is an example adding multiple groups from the `useradd-example.bb` file in the `meta-skeleton` layer:

```
GROUPADD_PARAM:${PN} = "-g 880 group1; -g 890 group2"
```

For information on the standard Linux shell command `groupadd`, see *groupadd(8)*.

### ***GRUB\_GFXSERIAL***

Configures the GNU GRand Unified Bootloader (GRUB) to have graphics and serial in the boot menu. Set this variable to "1" in your *build/conf/local.conf* or distribution *configuration file* to enable graphics and serial in the menu.

See the *grub-efi* class for more information on how this variable is used.

### ***GRUB\_MKIMAGE\_OPTS***

This variable controls additional options passed to the `grub-mkimage` command in the GNU GRand Unified Bootloader (GRUB) recipe during the `do_mkimage` task.

### ***GRUB\_OPTS***

Additional options to add to the GNU GRand Unified Bootloader (GRUB) configuration. Use a semi-colon character (;) to separate multiple options.

The *GRUB\_OPTS* variable is optional. See the *grub-efi* class for more information on how this variable is used.

### ***GRUB\_TIMEOUT***

Specifies the timeout before executing the default `LABEL` in the GNU GRand Unified Bootloader (GRUB).

The *GRUB\_TIMEOUT* variable is optional. See the *grub-efi* class for more information on how this variable is used.

### *GRUB\_TITLE*

Specifies custom titles for GRUB labels defined in *LABELS*. See the *grub-efi* class for more information on how this variable is used.

### *GTKIMMODULES\_PACKAGES*

When inheriting the *gtk-immodules-cache* class, this variable specifies the packages that contain the GTK+ input method modules being installed when the modules are in packages other than the main package.

### *HGDIR*

See *HGDIR* in the BitBake manual.

### *HOMEPAGE*

Website where more information about the software the recipe is building can be found.

### *HOST\_ARCH*

The name of the target architecture, which is normally the same as *TARGET\_ARCH*. The OpenEmbedded build system supports many architectures. Here is an example list of architectures supported. This list is by no means complete as the architecture is configurable:

- arm
- i586
- x86\_64
- powerpc
- powerpc64
- mips
- mipsel

### *HOST\_AS\_ARCH*

Specifies architecture-specific assembler flags.

Default initialization for *HOST\_AS\_ARCH* varies depending on what is being built:

- *TARGET\_AS\_ARCH* when building for the target
- *BUILD\_AS\_ARCH* when building for the build host (i.e. *-native*)
- *SDK\_AS\_ARCH* when building for an SDK (i.e. *nativesdk-*)

### *HOST\_CC\_ARCH*

Specifies architecture-specific compiler flags that are passed to the C compiler.

Default initialization for *HOST\_CC\_ARCH* varies depending on what is being built:

- *TARGET\_CC\_ARCH* when building for the target
- *BUILD\_CC\_ARCH* when building for the build host (i.e. *-native*)
- *SDK\_CC\_ARCH* when building for an SDK (i.e. *nativesdk-*)

### *HOST\_LD\_ARCH*

Specifies architecture-specific linker flags.

Default initialization for *HOST\_LD\_ARCH* varies depending on what is being built:



- *TARGET\_LD\_ARCH* when building for the target
- *BUILD\_LD\_ARCH* when building for the build host (i.e. `-native`)
- *SDK\_LD\_ARCH* when building for an SDK (i.e. `nativesdk-`)

### *HOST\_OS*

Specifies the name of the target operating system, which is normally the same as the *TARGET\_OS*. The variable can be set to "linux" for `glibc`-based systems and to "linux-musl" for `musl`. For ARM/EABI targets, there are also "linux-gnueabi" and "linux-musleabi" values possible.

### *HOST\_PREFIX*

Specifies the prefix for the cross-compile toolchain. *HOST\_PREFIX* is normally the same as *TARGET\_PREFIX*.

### *HOST\_SYS*

Specifies the system, including the architecture and the operating system, for which the build is occurring in the context of the current recipe.

The OpenEmbedded build system automatically sets this variable based on *HOST\_ARCH*, *HOST\_VENDOR*, and *HOST\_OS* variables.

#### **Nota**

You do not need to set the variable yourself.

Consider these two examples:

- Given a native recipe on a 32-bit x86 machine running Linux, the value is "i686-linux".
- Given a recipe being built for a little-endian MIPS target running Linux, the value might be "mipsel-linux".

### *HOST\_VENDOR*

Specifies the name of the vendor. *HOST\_VENDOR* is normally the same as *TARGET\_VENDOR*.

### *HOSTTOOLS*

A space-separated list (filter) of tools on the build host that should be allowed to be called from within build tasks. Using this filter helps reduce the possibility of host contamination. If a tool specified in the value of *HOSTTOOLS* is not found on the build host, the OpenEmbedded build system produces an error and the build is not started.

For additional information, see *HOSTTOOLS\_NONFATAL*.

### *HOSTTOOLS\_NONFATAL*

A space-separated list (filter) of tools on the build host that should be allowed to be called from within build tasks. Using this filter helps reduce the possibility of host contamination. Unlike *HOSTTOOLS*, the OpenEmbedded build system does not produce an error if a tool specified in the value of *HOSTTOOLS\_NONFATAL* is not found on the build host. Thus, you can use *HOSTTOOLS\_NONFATAL* to filter optional host tools.

### *IMAGE\_BASENAME*

The base name of image output files. This variable defaults to the recipe name (`${PN}`).

### IMAGE\_BOOT\_FILES

A space-separated list of files installed into the boot partition when preparing an image using the Wic tool with the `bootimg_partition` source plugin. By default, the files are installed under the same name as the source files. To change the installed name, separate it from the original name with a semi-colon (;). Source files need to be located in `DEPLOY_DIR_IMAGE`. Here are two examples:

```
IMAGE_BOOT_FILES = "u-boot.img uImage;kernel"
IMAGE_BOOT_FILES = "u-boot.${UBOOT_SUFFIX} ${KERNEL_IMAGETYPE}"
```

Alternatively, source files can be picked up using a glob pattern. In this case, the destination file must have the same name as the base name of the source file path. To install files into a directory within the target location, pass its name after a semi-colon (;). Here are two examples:

```
IMAGE_BOOT_FILES = "bcm2835-bootfiles/*"
IMAGE_BOOT_FILES = "bcm2835-bootfiles/*;boot/"
```

The first example installs all files from `${DEPLOY_DIR_IMAGE}/bcm2835-bootfiles` into the root of the target partition. The second example installs the same files into a `boot` directory within the target partition.

You can find information on how to use the Wic tool in the "[Creating Partitioned Images Using Wic](#)" section of the Yocto Project Development Tasks Manual. Reference material for Wic is located in the "[OpenEmbedded Kickstart \(.wks\) Reference](#)" chapter.

### IMAGE\_BUILDINFO\_FILE

When using the *image-buildinfo* class, specifies the file in the image to write the build information into. The default value is `"${sysconfdir}/buildinfo"`.

### IMAGE\_BUILDINFO\_VARS

When using the *image-buildinfo* class, specifies the list of variables to include in the *Build Configuration* section of the output file (as a space-separated list). Defaults to `"DISTRO DISTRO_VERSION"`.

### IMAGE\_CLASSES

A list of classes that all images should inherit. This is typically used to enable functionality across all image recipes.

Classes specified in `IMAGE_CLASSES` must be located in the `classes-recipe/` or `classes/` subdirectories.

### IMAGE\_CMD

Specifies the command to create the image file for a specific image type, which corresponds to the value set in `IMAGE_FSTYPES`, (e.g. `ext3`, `btrfs`, and so forth). When setting this variable, you should use an override for the associated type. Here is an example:

```
IMAGE_CMD:jffs2 = "mkfs.jffs2 --root=${IMAGE_ROOTFS} --faketime \
--output=${IMGDEPLOYDIR}/${IMAGE_NAME}${IMAGE_NAME_SUFFIX}.jffs2 \
${EXTRA_IMAGECMD}"
```

You typically do not need to set this variable unless you are adding support for a new image type. For more examples on how to set this variable, see the *image\_types* class file, which is `meta/classes-recipe/image_types.bbclass`.

### IMAGE\_CONTAINER\_NO\_DUMMY

When an image recipe has the `container` image type in *IMAGE\_FSTYPES*, it expects the *PREFERRED\_PROVIDER* for the Linux kernel (`virtual/kernel`) to be set to `linux-dummy` from a *configuration file*. Otherwise, an error is triggered.

When set to "1", the *IMAGE\_CONTAINER\_NO\_DUMMY* variable allows the *PREFERRED\_PROVIDER* variable to be set to another value, thus skipping the check and not triggering the build error. Any other value will keep the check.

This variable should be set from the image recipe using the `container` image type.

See the documentation of the *image-container* class for more information on why setting the *PREFERRED\_PROVIDER* to `linux-dummy` is advised with this class.

### IMAGE\_DEVICE\_TABLES

Specifies one or more files that contain custom device tables that are passed to the `makedevs` command as part of creating an image. These files list basic device nodes that should be created under `/dev` within the image. If *IMAGE\_DEVICE\_TABLES* is not set, `files/device_table-minimal.txt` is used, which is located by *BBPATH*. For details on how you should write device table files, see `meta/files/device_table-minimal.txt` as an example.

### IMAGE\_EFI\_BOOT\_FILES

A space-separated list of files installed into the boot partition when preparing an image using the Wic tool with the `bootimg_efi` source plugin. By default, the files are installed under the same name as the source files. To change the installed name, separate it from the original name with a semi-colon (;). Source files need to be located in *DEPLOY\_DIR\_IMAGE*. Here are two examples:

```
IMAGE_EFI_BOOT_FILES = "${KERNEL_IMAGETYPE};bz2"
IMAGE_EFI_BOOT_FILES = "${KERNEL_IMAGETYPE} microcode.cpio"
```

Alternatively, source files can be picked up using a glob pattern. In this case, the destination file must have the same name as the base name of the source file path. To install files into a directory within the target location, pass its name after a semi-colon (;). Here are two examples:

```
IMAGE_EFI_BOOT_FILES = "boot/loader/*"
IMAGE_EFI_BOOT_FILES = "boot/loader/*;boot/"
```

The first example installs all files from `${DEPLOY_DIR_IMAGE}/boot/loader/` into the root of the target partition. The second example installs the same files into a `boot` directory within the target partition.

You can find information on how to use the Wic tool in the "*Creating Partitioned Images Using Wic*" section of the Yocto Project Development Tasks Manual. Reference material for Wic is located in the "*OpenEmbedded Kickstart (.wks) Reference*" chapter.

### IMAGE\_EXTRA\_PARTITION\_FILES

A space-separated list of files installed into the extra partition(s) when preparing an image using the Wic tool with the `extra_partition` source plugin. By default, the files are installed under the same name as the source files. To change the installed name, separate it from the original name with a semi-colon (;). Source files need to be located in *DEPLOY\_DIR\_IMAGE*. Here is an example:

```
IMAGE_EXTRA_PARTITION_FILES = "foobar file.conf;config"
```

In the above example, the file `foobar` is installed with its original name `foobar`, while the file `file.conf` is installed and renamed to `config`.

Alternatively, source files can be picked up using a glob pattern. However, hidden files are ignored, and the pattern is non-recursive (subdirectories are ignored). The destination file will have the same name as the base name of the source file path. To install files into a renamed directory within the target location, pass its name after a semi-colon (;). Here are two examples:

```
IMAGE_EXTRA_PARTITION_FILES = "foo/*"
IMAGE_EXTRA_PARTITION_FILES = "foo/*;bar/"
```

The first line in this example installs all files from `foo` directory into the root of the target partition. The second line in this example installs the same files into a `bar` directory within the target partition. The `bar/` directory is automatically created if it does not exist.

You can also specify the target by label, UUID or partition name if multiple extra partitions coexist. Let's take the following example. This would be the WKS file for the image currently being built:

```
part --source extra_partition --fstype=ext4 --label foo
part --source extra_partition --fstype=ext4 --uuid e7d0824e-cda3-4bed-9f54-
→9ef5312d105d
part --source extra_partition --fstype=ext4 --part-name config
```

And the following configuration:

```
IMAGE_EXTRA_PARTITION_FILES_label-foo = "foo/*"
IMAGE_EXTRA_PARTITION_FILES_uuid-e7d0824e-cda3-4bed-9f54-9ef5312d105d = "foo/*;
→bar/"
IMAGE_EXTRA_PARTITION_FILES_part-name-config = "config"
```

Then:

- The partition labeled "foo" would get all files from the `foo` directory.
- The partition whose UUID is "e7d0824e-cda3-4bed-9f54-9ef5312d105d" would get all files from the `foo` directory, installed into a `bar` directory.
- The partition named "config" would get the file `config`.

You can find information on how to use the Wic tool in the "[Creating Partitioned Images Using Wic](#)" section of the Yocto Project Development Tasks Manual. Reference material for Wic is located in the "[OpenEmbedded Kickstart \(.wks\) Reference](#)" chapter.

## IMAGE\_FEATURES

The primary list of features to include in an image. Typically, you configure this variable in an image recipe. Although you can use this variable from your `build/conf/local.conf` file, which is found in the [Build Directory](#), best practices dictate that you do not.

**i Nota**

To enable extra features from outside the image recipe, use the *EXTRA\_IMAGE\_FEATURES* variable.

For a list of image features that ships with the Yocto Project, see the "*Image Features*" section.

For an example that shows how to customize your image by using this variable, see the "*Customizing Images Using Custom IMAGE\_FEATURES and EXTRA\_IMAGE\_FEATURES*" section in the Yocto Project Development Tasks Manual.

**IMAGE\_FSTYPES**

Specifies the formats the OpenEmbedded build system uses during the build when creating the root filesystem. For example, setting *IMAGE\_FSTYPES* as follows causes the build system to create root filesystems using two formats: *.ext3* and *.tar.bz2*:

```
IMAGE_FSTYPES = "ext3 tar.bz2"
```

For the complete list of supported image formats from which you can choose, see *IMAGE\_TYPES*.

**i Nota**

- If an image recipe uses the "inherit image" line and you are setting *IMAGE\_FSTYPES* inside the recipe, you must set *IMAGE\_FSTYPES* prior to using the "inherit image" line.
- Due to the way the OpenEmbedded build system processes this variable, you cannot update its contents by using `:append` or `:prepend`. You must use the `+=` operator to add one or more options to the *IMAGE\_FSTYPES* variable.

**IMAGE\_FSTYPES\_DEBUGFS**

The *IMAGE\_FSTYPES\_DEBUGFS* holds a list of filesystem image types to generate when the *IMAGE\_GEN\_DEBUGFS* variable is set to "1". The content of this variable is the same as what is supported by the *IMAGE\_FSTYPES* variable.

**IMAGE\_GEN\_DEBUGFS**

When set to "1" in an *image* recipe, the *OpenEmbedded Build System* will generate a companion image that contains the debug symbols and source code for the packages installed on the image. The *OpenEmbedded Build System* does this by adding all the available `-dbg` and `-src` packages available in the package feed, which are automatically generated during *Suddivisione in Pacchetti*.

**IMAGE\_INSTALL**

Used by recipes to specify the packages to install into an image through the *image* class. Use the *IMAGE\_INSTALL* variable with care to avoid ordering issues.

Image recipes set *IMAGE\_INSTALL* to specify the packages to install into an image through *image*. Additionally, there are "helper" classes such as the *core-image* class which can take lists used with *IMAGE\_FEATURES* and turn them into auto-generated entries in *IMAGE\_INSTALL* in addition to its default contents.

When you use this variable, it is best to use it as follows:

```
IMAGE_INSTALL:append = " package-name"
```

Be sure to include the space between the quotation character and the start of the package name or names.

#### **i** Nota

- When working with a *core-image-minimal-initramfs* image, do not use the *IMAGE\_INSTALL* variable to specify packages for installation. Instead, use the *PACKAGE\_INSTALL* variable, which allows the initial RAM filesystem (*Initramfs*) recipe to use a fixed set of packages and not be affected by *IMAGE\_INSTALL*. For information on creating an *Initramfs*, see the "*Building an Initial RAM Filesystem (Initramfs) Image*" section in the Yocto Project Development Tasks Manual.
- Using *IMAGE\_INSTALL* with the += BitBake operator within the *build/conf/local.conf* file or from within an image recipe is not recommended. Use of this operator in these ways can cause ordering issues. Since *core-image* sets *IMAGE\_INSTALL* to a default value using the += operator, using a += operation against *IMAGE\_INSTALL* results in unexpected behavior when used within *build/conf/local.conf*. Furthermore, the same operation from within an image recipe may or may not succeed depending on the specific situation. In both these cases, the behavior is contrary to how most users expect the += operator to work.

## *IMAGE\_LINGUAS*

Specifies the list of locales to install into the image during the root filesystem construction process. The OpenEmbedded build system automatically splits locale files, which are used for localization, into separate packages. Setting the *IMAGE\_LINGUAS* variable ensures that any locale packages that correspond to packages already selected for installation into the image are also installed. Here is an example:

```
IMAGE_LINGUAS = "pt-br de-de"
```

In this example, the build system ensures any Brazilian Portuguese and German locale files that correspond to packages in the image are installed (i.e. \*-locale-pt-br and \*-locale-de-de as well as \*-locale-pt and \*-locale-de, since some software packages only provide locale files by language and not by country-specific language).

See the *GLIBC\_GENERATE\_LOCALES* variable for information on generating GLIBC locales.

## *IMAGE\_LINK\_NAME*

The name of the output image symlink (which does not include the version part as *IMAGE\_NAME* does). The default value is derived using the *IMAGE\_BASENAME* and *IMAGE\_MACHINE\_SUFFIX* variables:

```
IMAGE_LINK_NAME ?= "${IMAGE_BASENAME}${IMAGE_MACHINE_SUFFIX}"
```

#### **i** Nota

It is possible to set this to "" to disable symlink creation, however, you also need to set *IMAGE\_NAME* to still have a reasonable value e.g.:

```
IMAGE_LINK_NAME = ""
IMAGE_NAME = "${IMAGE_BASENAME}${IMAGE_MACHINE_SUFFIX}${IMAGE_VERSION_
↪ SUFFIX}"
```

### IMAGE\_MACHINE\_SUFFIX

Specifies the by default machine-specific suffix for image file names (before the extension). The default value is set as follows:

```
IMAGE_MACHINE_SUFFIX ??= "-${MACHINE}"
```

The default *DEPLOY\_DIR\_IMAGE* already has a *MACHINE* subdirectory, so you may find it unnecessary to also include this suffix in the name of every image file. If you prefer to remove the suffix you can set this variable to an empty string:

```
IMAGE_MACHINE_SUFFIX = ""
```

(Not to be confused with *IMAGE\_NAME\_SUFFIX*.)

### IMAGE\_MANIFEST

The manifest file for the image. This file lists all the installed packages that make up the image. The file contains package information on a line-per-package basis as follows:

```
packagename packagearch version
```

The *rootfs-postcommands* class defines the manifest file as follows:

```
IMAGE_MANIFEST = "${IMGDEPLOYDIR}/${IMAGE_NAME}${IMAGE_NAME_SUFFIX}.manifest"
```

The location is derived using the *IMGDEPLOYDIR* and *IMAGE\_NAME* variables. You can find information on how the image is created in the "*Generazione dell'Immagine*" section in the Yocto Project Overview and Concepts Manual.

### IMAGE\_NAME

The name of the output image files minus the extension. By default this variable is set using the *IMAGE\_LINK\_NAME*, and *IMAGE\_VERSION\_SUFFIX* variables:

```
IMAGE_NAME ?= "${IMAGE_LINK_NAME}${IMAGE_VERSION_SUFFIX}"
```

### IMAGE\_NAME\_SUFFIX

Suffix used for the image output filename --- defaults to ".rootfs" to distinguish the image file from other files created during image building; however if this suffix is redundant or not desired you can clear the value of this variable (set the value to ""). For example, this is typically cleared in *Initramfs* image recipes.

### IMAGE\_OUTPUT\_MANIFEST

When inheriting the *image* class directly or through the *core-image* class, the *IMAGE\_OUTPUT\_MANIFEST* points to a manifest *json* file that lists what images were created by various image creation tasks (as defined by the *IMAGE\_FSTYPES* variable). It is set in the *image* class as follows:

```
IMAGE_OUTPUT_MANIFEST = "${IMAGE_OUTPUT_MANIFEST_DIR}/manifest.json"
```

### **IMAGE\_OUTPUT\_MANIFEST\_DIR**

When inheriting the *image* class directly or through the *core-image* class, the *IMAGE\_OUTPUT\_MANIFEST\_DIR* points to a directory that stores a manifest json file that lists what images were created by various image creation tasks (as defined by the *IMAGE\_FSTYPES* variable). It is set in the *image* class as follows:

```
IMAGE_OUTPUT_MANIFEST_DIR = "${WORKDIR}/deploy-image-output-manifest"
```

### **IMAGE\_OVERHEAD\_FACTOR**

Defines a multiplier that the build system applies to the initial image size for cases when the multiplier times the returned disk usage value for the image is greater than the sum of *IMAGE\_ROOTFS\_SIZE* and *IMAGE\_ROOTFS\_EXTRA\_SPACE*. The result of the multiplier applied to the initial image size creates free disk space in the image as overhead. By default, the build process uses a multiplier of 1.3 for this variable. This default value results in 30% free disk space added to the image when this method is used to determine the final generated image size. You should be aware that post install scripts and the package management system uses disk space inside this overhead area. Consequently, the multiplier does not produce an image with all the theoretical free disk space. See *IMAGE\_ROOTFS\_SIZE* for information on how the build system determines the overall image size.

The default 30% free disk space typically gives the image enough room to boot and allows for basic post installs while still leaving a small amount of free disk space. If 30% free space is inadequate, you can increase the default value. For example, the following setting gives you 50% free space added to the image:

```
IMAGE_OVERHEAD_FACTOR = "1.5"
```

Alternatively, you can ensure a specific amount of free disk space is added to the image by using the *IMAGE\_ROOTFS\_EXTRA\_SPACE* variable.

When using Wic tool, beware that a second overhead factor is also applied. This overhead value is defined by the `--overhead-factor` option, which defaults to "1.3" when omitted. See the *Command: part or partition* chapter in *OpenEmbedded Kickstart (.wks) Reference* for details.

### **IMAGE\_PKGTYPE**

Defines the package type (i.e. DEB, RPM or IPK) used by the OpenEmbedded build system. The variable is defined appropriately by one of the *package\_deb*, *package\_rpm*, or *package\_ipk* classes.

The *populate\_sdk\_\** and *image* classes use the *IMAGE\_PKGTYPE* for packaging images and SDKs.

You should not set the *IMAGE\_PKGTYPE* manually. Rather, the variable is set indirectly through the appropriate *package\_\** class using the *PACKAGE\_CLASSES* variable. The OpenEmbedded build system uses the first package type (e.g. DEB, RPM, or IPK) that appears with the variable

### **IMAGE\_POSTPROCESS\_COMMAND**

Specifies a list of functions to call once the OpenEmbedded build system creates the final image output files. You can specify functions separated by spaces:



```
IMAGE_POSTPROCESS_COMMAND += "function"
```

If you need to pass the root filesystem path to a command within the function, you can use `${IMAGE_ROOTFS}`, which points to the directory that becomes the root filesystem image. See the [IMAGE\\_ROOTFS](#) variable for more information.

### **IMAGE\_PREPROCESS\_COMMAND**

Specifies a list of functions to call before the OpenEmbedded build system creates the final image output files. You can specify functions separated by spaces:

```
IMAGE_PREPROCESS_COMMAND += "function"
```

If you need to pass the root filesystem path to a command within the function, you can use `${IMAGE_ROOTFS}`, which points to the directory that becomes the root filesystem image. See the [IMAGE\\_ROOTFS](#) variable for more information.

### **IMAGE\_ROOTFS**

The location of the root filesystem while it is under construction (i.e. during the [do\\_rootfs](#) task). This variable is not configurable. Do not change it.

### **IMAGE\_ROOTFS\_ALIGNMENT**

Specifies the alignment for the output image file in Kbytes. If the size of the image is not a multiple of this value, then the size is rounded up to the nearest multiple of the value. The default value is "1". See [IMAGE\\_ROOTFS\\_SIZE](#) for additional information.

### **IMAGE\_ROOTFS\_EXTRA\_SPACE**

Defines additional free disk space created in the image in Kbytes. By default, this variable is set to "0". This free disk space is added to the image after the build system determines the image size as described in [IMAGE\\_ROOTFS\\_SIZE](#).

This variable is particularly useful when you want to ensure that a specific amount of free disk space is available on a device after an image is installed and running. For example, to be sure 5 Gbytes of free disk space is available, set the variable as follows:

```
IMAGE_ROOTFS_EXTRA_SPACE = "5242880"
```

For example, the Yocto Project Build Appliance specifically requests 40 Gbytes of extra space with the line:

```
IMAGE_ROOTFS_EXTRA_SPACE = "41943040"
```

### **IMAGE\_ROOTFS\_MAXSIZE**

Defines the maximum allowed size of the generated image in kilobytes. The build will fail if the generated image size exceeds this value.

The generated image size undergoes several calculation steps before being compared to [IMAGE\\_ROOTFS\\_MAXSIZE](#). In the first step, the size of the directory pointed to by [IMAGE\\_ROOTFS](#) is calculated. In the second step, the result from the first step is multiplied by [IMAGE\\_OVERHEAD\\_FACTOR](#). In the third step, the result from the second step is compared with [IMAGE\\_ROOTFS\\_SIZE](#). The larger value of these is added to [IMAGE\\_ROOTFS\\_EXTRA\\_SPACE](#). In the fourth step, the result from the third step is checked for a

decimal part. If it has one, it is rounded up to the next integer. If it does not, it is simply converted into an integer. In the fifth step, the `IMAGE_ROOTFS_ALIGNMENT` is added to the result from the fourth step and "1" is subtracted. In the sixth step, the remainder of the division between the result from the fifth step and `IMAGE_ROOTFS_ALIGNMENT` is subtracted from the result of the fifth step. In this way, the result from the fourth step is rounded up to the nearest multiple of `IMAGE_ROOTFS_ALIGNMENT`.

Thus, if the `IMAGE_ROOTFS_MAXSIZE` is set, is compared with the result of the above calculations and is independent of the final image type. No default value is set for `IMAGE_ROOTFS_MAXSIZE`.

It's a good idea to set this variable for images that need to fit on a limited space (e.g. SD card, a fixed-size partition, ...).

### `IMAGE_ROOTFS_SIZE`

Defines the size in Kbytes for the generated image. The OpenEmbedded build system determines the final size for the generated image using an algorithm that takes into account the initial disk space used for the generated image, a requested size for the image, and requested additional free disk space to be added to the image. Programatically, the build system determines the final size of the generated image as follows:

```
if (image-du * overhead) < rootfs-size:
    internal-rootfs-size = rootfs-size + xspace
else:
    internal-rootfs-size = (image-du * overhead) + xspace
where:
    image-du = Returned value of the du command on the image.
    overhead = IMAGE_OVERHEAD_FACTOR
    rootfs-size = IMAGE_ROOTFS_SIZE
    internal-rootfs-size = Initial root filesystem size before any
    ↪ modifications.
    xspace = IMAGE_ROOTFS_EXTRA_SPACE
```

See the `IMAGE_OVERHEAD_FACTOR` and `IMAGE_ROOTFS_EXTRA_SPACE` variables for related information.

### `IMAGE_TYPEDEP`

Specifies a dependency from one image type on another. Here is an example from the `image-live` class:

```
IMAGE_TYPEDEP:live = "ext3"
```

In the previous example, the variable ensures that when "live" is listed with the `IMAGE_FSTYPES` variable, the OpenEmbedded build system produces an `ext3` image first since one of the components of the live image is an `ext3` formatted partition containing the root filesystem.

### `IMAGE_TYPES`

Specifies the complete list of supported image types by default:

- `btrfs`
- `container`
- `cpio`

- cpio.gz
- cpio.lz4
- cpio.lzma
- cpio.xz
- cramfs
- erofs
- erofs-lz4
- erofs-lz4hc
- ext2
- ext2.bz2
- ext2.gz
- ext2.lzma
- ext3
- ext3.gz
- ext4
- ext4.gz
- f2fs
- hddimg
- iso
- jffs2
- jffs2.sum
- multiubi
- squashfs
- squashfs-lz4
- squashfs-lzo
- squashfs-xz
- tar
- tar.bz2
- tar.gz
- tar.lz4
- tar.xz
- tar.zst

- ubi
- ubifs
- wic
- wic.bz2
- wic.gz
- wic.lzma
- wic.zst
- wicenv

For more information about these types of images, see `meta/classes-recipe/image_types*.bbclass` in *OpenEmbedded-Core (OE-Core)*.

### *IMAGE\_VERSION\_SUFFIX*

Version suffix that is part of the default *IMAGE\_NAME* and *KERNEL\_ARTIFACT\_NAME* values. Defaults to `"-${DATETIME}"`, however you could set this to a version string that comes from your external build environment if desired, and this suffix would then be used consistently across the build artifacts.

### *IMGDEPLOYDIR*

When inheriting the *image* class directly or through the *core-image* class, the *IMGDEPLOYDIR* points to a temporary work area for deployed files that is set in the *image* class as follows:

```
IMGDEPLOYDIR = "${WORKDIR}/deploy-${PN}-image-complete"
```

Recipes inheriting the *image* class should copy files to be deployed into *IMGDEPLOYDIR*, and the class will take care of copying them into *DEPLOY\_DIR\_IMAGE* afterwards.

### *IMGMANIFESTDIR*

When inheriting the *image* class directly or through the *core-image* class, the *IMGMANIFESTDIR* setting points to a temporary area that stores manifest `json` files, that list what images were created by various images creation tasks (as defined by the *IMAGE\_FSTYPES* variable). It is set in the *image* class as follows:

```
IMGMANIFESTDIR = "${WORKDIR}/image-task-manifest"
```

### *INCOMPATIBLE\_LICENSE*

Specifies a space-separated list of license names (as they would appear in *LICENSE*) that should be excluded from the build (if set globally), or from an image (if set locally in an image recipe).

When the variable is set globally, recipes that provide no alternatives to listed incompatible licenses are not built. Packages that are individually licensed with the specified incompatible licenses will be deleted. Most of the time this does not allow a feasible build (because it becomes impossible to satisfy build time dependencies), so the recommended way to implement license restrictions is to set the variable in specific image recipes where the restrictions must apply. That way there are no build time restrictions, but the license check is still performed when the image's filesystem is assembled from packages.

There is some support for wildcards in this variable's value, however it is restricted to specific licenses. Currently only these wildcards are allowed and expand as follows:

- AGPL-3.0\*: AGPL-3.0-only, AGPL-3.0-or-later
- GPL-3.0\*: GPL-3.0-only, GPL-3.0-or-later
- LGPL-3.0\*: LGPL-3.0-only, LGPL-3.0-or-later

If a license in *LICENSE* has an exception listed using the `WITH` operator, the license will still match this variable and the license will not be allowed. To explicitly allow an SPDX license exception to a license, the exception must be listed in *INCOMPATIBLE\_LICENSE\_EXCEPTIONS*

#### Nota

This functionality is only regularly tested using the following setting:

```
INCOMPATIBLE_LICENSE = "GPL-3.0* LGPL-3.0* AGPL-3.0"
```

Although you can use other settings, you might be required to remove dependencies on (or provide alternatives to) components that are required to produce a functional system image.

### *INCOMPATIBLE\_LICENSE\_EXCEPTIONS*

Specifies a space-separated list of package and SPDX license or SPDX license exception pairs that are allowed to be used even if the license is specified in *INCOMPATIBLE\_LICENSE*. The package and license pairs are separated using a colon. Example:

```
INCOMPATIBLE_LICENSE_EXCEPTIONS = "gdbserver:GPL-3.0-only gdbserver:LGPL-3.0-
↳only gcc:GCC-exception-3.1"
```

### *INHERIT*

Causes the named class or classes to be inherited globally. Anonymous functions in the class or classes are not executed for the base configuration and in each individual recipe. The OpenEmbedded build system ignores changes to *INHERIT* in individual recipes. Classes inherited using *INHERIT* must be located in the `classes-global/` or `classes/` subdirectories.

For more information on *INHERIT*, see the *INHERIT Configuration Directive* section in the BitBake User Manual.

### *INHERIT\_DISTRO*

Lists classes that will be inherited at the distribution level. It is unlikely that you want to edit this variable.

Classes specified in *INHERIT\_DISTRO* must be located in the `classes-global/` or `classes/` subdirectories.

The default value of the variable is set as follows in the `meta/conf/distro/defaultsetup.conf` file:

```
INHERIT_DISTRO ?= "debian devshell sstate license remove-libtool create-spdx"
```

### *INHIBIT\_AUTOTOOLS\_DEPS*

Prevents the *autotools\** class from automatically adding its default build-time dependencies.

When a recipe inherits the *autotools\** class, several native cross tools such as `autoconf-native`, `automake-native`, `libtool-native`, `libtool-cross` are added to *DEPENDS* to support the *autotools* build process.

To prevent the build system from adding these dependencies automatically, set the *INHIBIT\_AUTOTOOLS\_DEPS* variable as follows:

```
INHIBIT_AUTOTOOLS_DEPS = "1"
```

By default, the value of *INHIBIT\_AUTOTOOLS\_DEPS* is empty. Setting it to "0" does not disable inhibition. Only the empty string will disable inhibition.

### *INHIBIT\_DEFAULT\_DEPS*

Prevents the default dependencies, namely the C compiler and standard C library (libc), from being added to *DEPENDS*. This variable is usually used within recipes that do not require any compilation using the C compiler.

Set the variable to "1" to prevent the default dependencies from being added.

### *INHIBIT\_DEFAULT\_RUST\_DEPS*

Prevents the *rust* class from automatically adding its default build-time dependencies.

When a recipe inherits the *rust* class, several tools such as *rust-native* and *\${RUSTLIB\_DEP}* (only added when cross-compiling) are added to *DEPENDS* to support the *rust* build process.

To prevent the build system from adding these dependencies automatically, set the *INHIBIT\_DEFAULT\_RUST\_DEPS* variable as follows:

```
INHIBIT_DEFAULT_RUST_DEPS = "1"
```

By default, the value of *INHIBIT\_DEFAULT\_RUST\_DEPS* is empty. Setting it to "0" does not disable inhibition. Only the empty string will disable inhibition.

### *INHIBIT\_PACKAGE\_DEBUG\_SPLIT*

Prevents the OpenEmbedded build system from splitting out debug information during packaging. By default, the build system splits out debugging information during the *do\_package* task. For more information on how debug information is split out, see the *PACKAGE\_DEBUG\_SPLIT\_STYLE* variable.

To prevent the build system from splitting out debug information during packaging, set the *INHIBIT\_PACKAGE\_DEBUG\_SPLIT* variable as follows:

```
INHIBIT_PACKAGE_DEBUG_SPLIT = "1"
```

### *INHIBIT\_PACKAGE\_STRIP*

If set to "1", causes the build to not strip binaries in resulting packages and prevents the *-dbg* package from containing the source files.

By default, the OpenEmbedded build system strips binaries and puts the debugging symbols into *\${PN}-dbg*. Consequently, you should not set *INHIBIT\_PACKAGE\_STRIP* when you plan to debug in general.

### *INHIBIT\_SYSROOT\_STRIP*

If set to "1", causes the build to not strip binaries in the resulting sysroot.

By default, the OpenEmbedded build system strips binaries in the resulting sysroot. When you specifically set the *INHIBIT\_SYSROOT\_STRIP* variable to "1" in your recipe, you inhibit this stripping.

If you want to use this variable, include the *staging* class. This class uses a `sys_strip()` function to test for the variable and acts accordingly.

#### **Nota**

Use of the *INHIBIT\_SYSROOT\_STRIP* variable occurs in rare and special circumstances. For example, suppose you are building bare-metal firmware by using an external GCC toolchain. Furthermore, even if the toolchain's binaries are strippable, there are other files needed for the build that are not strippable.

### *INHIBIT\_UPDATERCD\_BBCLASS*

Prevents the *update-rc.d* class from automatically installing and registering SysV init scripts for packages.

When a recipe inherits the *update-rc.d* class, init scripts are typically installed and registered for the packages listed in *INITSCRIPT\_PACKAGES*. This ensures that the relevant services are started and stopped at the appropriate runlevels using the traditional SysV init system.

To prevent the build system from adding these scripts and configurations automatically, set the *INHIBIT\_UPDATERCD\_BBCLASS* variable as follows:

```
INHIBIT_UPDATERCD_BBCLASS = "1"
```

By default, the value of *INHIBIT\_UPDATERCD\_BBCLASS* is empty. Setting it to "0" does not disable inhibition. Only the empty string will disable inhibition.

### *INIT\_MANAGER*

Specifies the system init manager to use. Available options are:

- `sysvinit`
- `systemd`
- `mdev-busybox`

With `sysvinit`, the init manager is set to *SysVinit*, the traditional UNIX init system. This is the default choice in the *Poky* distribution, together with the Udev device manager (see the "*Selecting a Device Manager*" section).

With `systemd`, the init manager becomes *systemd*, which comes with the *udev* device manager.

With `mdev-busybox`, the init manager becomes the much simpler BusyBox init, together with the BusyBox *mdev* device manager. This is the simplest and lightest solution, and probably the best choice for low-end systems with a rather slow CPU and a limited amount of RAM.

More concretely, this is used to include `conf/distro/include/init-manager-${INIT_MANAGER}.inc` into the global configuration. You can have a look at the `meta/conf/distro/include/init-manager-*.inc` files for more information, and also the "*Selecting an Initialization Manager*" section in the Yocto Project Development Tasks Manual.

### *INITRAMFS\_DEPLOY\_DIR\_IMAGE*

Indicates the deploy directory used by *do\_bundle\_initramfs* where the *INITRAMFS\_IMAGE* will be fetched from. This variable is set by default to `${DEPLOY_DIR_IMAGE}` in the *kernel* class and it's only meant to be changed when building an *Initramfs* image from a separate multiconfig via *INITRAMFS\_MULTICONFIG*.

### INITRAMFS\_FSTYPES

Defines the format for the output image of an initial RAM filesystem (*Initramfs*), which is used during boot. Supported formats are the same as those supported by the *IMAGE\_FSTYPES* variable.

The default value of this variable, which is set in the `meta/conf/bitbake.conf` configuration file in *OpenEmbedded-Core (OE-Core)*, is "cpio.gz". The Linux kernel's *Initramfs* mechanism, as opposed to the initial RAM filesystem *initrd* mechanism, expects an optionally compressed cpio archive.

### INITRAMFS\_IMAGE

Specifies the *PROVIDES* name of an image recipe that is used to build an initial RAM filesystem (*Initramfs*) image. In other words, the *INITRAMFS\_IMAGE* variable causes an additional recipe to be built as a dependency to whatever root filesystem recipe you might be using (e.g. `core-image-sato`). The *Initramfs* image recipe you provide should set *IMAGE\_FSTYPES* to *INITRAMFS\_FSTYPES*.

An *Initramfs* image provides a temporary root filesystem used for early system initialization (e.g. loading of modules needed to locate and mount the "real" root filesystem).

#### Nota

See the `meta/recipes-core/images/core-image-minimal-initramfs.bb` recipe in *OpenEmbedded-Core (OE-Core)* for an example *Initramfs* recipe. To select this sample recipe as the one built to provide the *Initramfs* image, set *INITRAMFS\_IMAGE* to "core-image-minimal-initramfs".

You can also find more information by referencing the `meta/conf/templates/default/local.conf.sample.extended` configuration file in *OpenEmbedded-Core (OE-Core)*, the *image* class, and the *kernel* class to see how to use the *INITRAMFS\_IMAGE* variable.

If *INITRAMFS\_IMAGE* is empty, which is the default, then no *Initramfs* image is built.

For more information, you can also see the *INITRAMFS\_IMAGE\_BUNDLE* variable, which allows the generated image to be bundled inside the kernel image. Additionally, for information on creating an *Initramfs* image, see the "*Building an Initial RAM Filesystem (Initramfs) Image*" section in the Yocto Project Development Tasks Manual.

### INITRAMFS\_IMAGE\_BUNDLE

Controls whether or not the image recipe specified by *INITRAMFS\_IMAGE* is run through an extra pass (*do\_bundle\_initramfs*) during kernel compilation in order to build a single binary that contains both the kernel image and the initial RAM filesystem (*Initramfs*) image. This makes use of the *CONFIG\_INITRAMFS\_SOURCE* kernel feature.

#### Nota

Bundling the *Initramfs* with the kernel conflates the code in the *Initramfs* with the GPLv2 licensed Linux kernel binary. Thus only GPLv2 compatible software may be part of a bundled *Initramfs*.



**i Nota**

Using an extra compilation pass to bundle the *Initramfs* avoids a circular dependency between the kernel recipe and the *Initramfs* recipe should the *Initramfs* include kernel modules. Should that be the case, the *Initramfs* recipe depends on the kernel for the kernel modules, and the kernel depends on the *Initramfs* recipe since the *Initramfs* is bundled inside the kernel image.

The combined binary is deposited into the `tmp/deploy` directory, which is part of the *Build Directory*.

Setting the variable to "1" in a configuration file causes the OpenEmbedded build system to generate a kernel image with the *Initramfs* specified in *INITRAMFS\_IMAGE* bundled within:

```
INITRAMFS_IMAGE_BUNDLE = "1"
```

By default, the *kernel* class sets this variable to a null string as follows:

```
INITRAMFS_IMAGE_BUNDLE ?= ""
```

**i Nota**

You must set the *INITRAMFS\_IMAGE\_BUNDLE* variable in a configuration file. You cannot set the variable in a recipe file.

See the `local.conf.sample.extended` file for additional information. Also, for information on creating an *Initramfs*, see the "*Building an Initial RAM Filesystem (Initramfs) Image*" section in the Yocto Project Development Tasks Manual.

**INITRAMFS\_IMAGE\_NAME**

This value needs to stay in sync with *IMAGE\_LINK\_NAME*, but with *INITRAMFS\_IMAGE* instead of *IMAGE\_BASENAME*. The default value is set as follows:

```
INITRAMFS_IMAGE_NAME ?= "${@[ '${INITRAMFS_IMAGE}'${IMAGE_MACHINE_SUFFIX} ],
[d.getVar('INITRAMFS_IMAGE') == '']}"
```

That is, if *INITRAMFS\_IMAGE* is set, the value of *INITRAMFS\_IMAGE\_NAME* will be set based upon *INITRAMFS\_IMAGE* and *IMAGE\_MACHINE\_SUFFIX*.

**INITRAMFS\_LINK\_NAME**

The link name of the initial RAM filesystem image. This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
INITRAMFS_LINK_NAME ?= "initramfs-${KERNEL_ARTIFACT_LINK_NAME}"
```

The value of the *KERNEL\_ARTIFACT\_LINK\_NAME* variable, which is set in the same file, has the following value:

```
KERNEL_ARTIFACT_LINK_NAME ?= "${MACHINE}"
```

See the *MACHINE* variable for additional information.

### *INITRAMFS\_MAXSIZE*

Defines the maximum allowed size of the *initramfs* image in Kbytes. The build will fail if the *initramfs* image size exceeds this value.

The *initramfs* image size undergoes several calculation steps before being compared to *INITRAMFS\_MAXSIZE*. These steps are the same as those used for *IMAGE\_ROOTFS\_MAXSIZE* and are described in detail in that entry.

Thus, *INITRAMFS\_MAXSIZE* is compared with the result of the calculations and is independent of the final image type (e.g. compressed). A default value for *INITRAMFS\_MAXSIZE* is set in `meta/conf/bitbake.conf`.

### *INITRAMFS\_MULTICONFIG*

Defines the multiconfig to create a multiconfig dependency to be used by the *kernel* class.

This allows the kernel to bundle an *INITRAMFS\_IMAGE* coming from a separate multiconfig, this is meant to be used in addition to *INITRAMFS\_DEPLOY\_DIR\_IMAGE*.

For more information on how to bundle an *initramfs* image from a separate multiconfig see the "*Bundling an initramfs Image From a Separate Multiconfig*" section in the Yocto Project Development Tasks Manual.

### *INITRAMFS\_NAME*

The base name of the initial RAM filesystem image. This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
INITRAMFS_NAME ?= "initramfs-${KERNEL_ARTIFACT_NAME}"
```

See *KERNEL\_ARTIFACT\_NAME* for additional information.

### *INITRD*

Indicates list of filesystem images to concatenate and use as an initial RAM disk (*initrd*).

The *INITRD* variable is an optional variable used with the *image-live* class.

### *INITRD\_IMAGE*

When building a "live" bootable image (i.e. when *IMAGE\_FSTYPES* contains "live"), *INITRD\_IMAGE* specifies the image recipe that should be built to provide the initial RAM disk image. The default value is "core-image-minimal-initramfs".

See the *image-live* class for more information.

### *INITSCRIPT\_NAME*

The filename of the initialization script as installed to `${sysconfdir}/init.d`.

This variable is used in recipes when using *update-rc.d*. The variable is mandatory.

### *INITSCRIPT\_PACKAGES*

A list of the packages that contain initscripts. If multiple packages are specified, you need to append the package name to the other *INITSCRIPT\_\** as an override.

This variable is used in recipes when using *update-rc.d*. The variable is optional and defaults to the *PN* variable.

### *INITSCRIPT\_PARAMS*

Specifies the options to pass to *update-rc.d*. Here is an example:

```
INITSCRIPT_PARAMS = "start 99 5 2 . stop 20 0 1 6 ."
```

In this example, the script has a runlevel of 99, starts the script in initlevels 2 and 5, and stops the script in levels 0, 1 and 6.

The variable's default value is "defaults", which is set in the *update-rc.d* class.

The value in *INITSCRIPT\_PARAMS* is passed through to the *update-rc.d* command. For more information on valid parameters, please see the manual page: *update-rc.d*.

### *INSANE\_SKIP*

Specifies the QA checks to skip for a specific package within a recipe. For example, to skip the check for symbolic link *.so* files in the main package of a recipe, add the following to the recipe. The package name override must be used, which in this example is *{PN}*:

```
INSANE_SKIP:${PN} += "dev-so"
```

See the "*insane*" section for a list of the valid QA checks you can specify using this variable.

### *INSTALL\_TIMEZONE\_FILE*

By default, the *tzdata* recipe packages an */etc/timezone* file. Set the *INSTALL\_TIMEZONE\_FILE* variable to "0" at the configuration level to disable this behavior.

### *IPK\_FEED\_URIS*

When the IPK backend is in use and package management is enabled on the target, you can use this variable to set up *opkg* in the target image to point to package feeds on a nominated server. Once the feed is established, you can perform installations or upgrades using the package manager at runtime.

### *KARCH*

Defines the kernel architecture used when assembling the configuration. Architectures supported for this release are:

- powerpc
- i386
- x86\_64
- arm
- qemu
- mips

You define the *KARCH* variable in the *BSP Descriptions*.

### *KBRANCH*

A regular expression used by the build process to explicitly identify the kernel branch that is validated, patched, and configured during a build. You must set this variable to ensure the exact kernel branch you want is being used by the build process.

Values for this variable are set in the kernel's recipe file and the kernel's append file. For example, if you are using the *linux-yocto\_4.12* kernel, the kernel recipe file is the *meta/recipes-kernel/linux/linux-yocto\_4.12.bb* file. *KBRANCH* is set as follows in that kernel recipe file:

```
KBRANCH ?= "standard/base"
```

This variable is also used from the kernel's append file to identify the kernel branch specific to a particular machine or target hardware. Continuing with the previous kernel example, the kernel's append file is located in the BSP layer for a given machine. For example, the append file for the Beaglebone and generic versions of both 32 and 64-bit IA machines (`meta-yocto-bsp`) is named `meta-yocto-bsp/recipes-kernel/linux/linux-yocto_6.1.bbappend`. Here are the related statements from that append file:

```
KBRANCH:genericx86 = "v6.1/standard/base"
KBRANCH:genericx86-64 = "v6.1/standard/base"
KBRANCH:beaglebone-yocto = "v6.1/standard/beaglebone"
```

The *KBRANCH* statements identify the kernel branch to use when building for each supported BSP.

### *KBUILD\_DEFCONFIG*

When used with the *kernel-yocto* class, specifies an "in-tree" kernel configuration file for use during a kernel build.

Typically, when using a `defconfig` to configure a kernel during a build, you place the file in your layer in the same manner as you would place patch files and configuration fragment files (i.e. "out-of-tree"). However, if you want to use a `defconfig` file that is part of the kernel tree (i.e. "in-tree"), you can use the *KBUILD\_DEFCONFIG* variable to point to the `defconfig` file.

To use the variable, set it in the append file for your kernel recipe using the following form:

```
KBUILD_DEFCONFIG:<machine> ?= "defconfig_file"
```

Here is an example from a "raspberrypi2" *MACHINE* build that uses a `defconfig` file named "bcm2709\_defconfig":

```
KBUILD_DEFCONFIG:raspberrypi2 = "bcm2709_defconfig"
```

As an alternative, you can use the following within your append file:

```
KBUILD_DEFCONFIG:pn-linux-yocto ?= "defconfig_file"
```

For more information on how to use the *KBUILD\_DEFCONFIG* variable, see the "Using an "In-Tree" `defconfig` File" section in the Yocto Project Linux Kernel Development Manual.

### *KCONF\_AUDIT\_LEVEL*

When inheriting the *kernel-yocto* class and when the *KMETA\_AUDIT* variable is set to a non-empty string, the *KCONF\_AUDIT\_LEVEL* variable specifies whether to report Kernel configuration values that are different from the user-specified value. Its value is a positive integer (default: 1):

- 0: no reporting is done.
- 1: report the problems as warnings and trigger an error if *KMETA\_AUDIT\_WERROR* is set.
- 2: if the *do\_kernel\_configme* has failed to generate a `.config` file, print the content of the `merge_config_build.log` file containing the errors, instead of just providing the path to that file.

For more details see the *kernel-yocto* class and the *symbol\_why.py* script in *yocto-kernel-tools*.

### ***KCONF\_BSP\_AUDIT\_LEVEL***

When inheriting the *kernel-yocto* class and when the *KMETA\_AUDIT* variable is set to a non-empty string, the *KCONF\_BSP\_AUDIT\_LEVEL* variable can be set to report:

1. User-specified Kernel configurations that did not make it into the final Kernel configuration.
2. Configurations defined in multiple input files with differing values.

Its value is a positive integer (default: 0):

- 0: no reporting is done.
- 1: reporting of configuration options that did not make it in the final configuration is done and is not limited to the current architecture (ARCH) in use.
- 2: reporting of configuration options that did not make it in the final configuration is done and is strictly limited to the current architecture (ARCH) in use.
- 3: report the problems found when this variable equals 2, and also report configurations options defined in multiple input files with differing values.

For value 1, 2 and 3 an error is produced if *KMETA\_AUDIT\_WERROR* is set.

For more details see the *kernel-yocto* class and the *symbol\_why.py* script in *yocto-kernel-tools*.

### ***KCONFIG\_CONFIG\_ROOTDIR***

The *KCONFIG\_CONFIG\_ROOTDIR* variable allows overriding the default location of the *.config* file for recipes using the *cml1* class.

### ***KCONFIG\_MODE***

When used with the *kernel-yocto* class, specifies the kernel configuration values to use for options not specified in the provided *defconfig* file. Valid options are:

```
KCONFIG_MODE = "alldefconfig"
KCONFIG_MODE = "allnoconfig"
```

In *alldefconfig* mode the options not explicitly specified will be assigned their Kconfig default value. In *allnoconfig* mode the options not explicitly specified will be disabled in the kernel config.

In case *KCONFIG\_MODE* is not set the *defconfig* file will be handled in *allnoconfig* mode.

A *defconfig* file compatible with *allnoconfig* mode can be generated by copying the *.config* file from a working Linux kernel build, renaming it to *defconfig* and placing it into the Linux kernel *\${WORKDIR}* through your meta-layer. *KCONFIG\_MODE* does not need to be explicitly set.

A *defconfig* file compatible with *alldefconfig* mode can be generated using the *do\_savedefconfig* task and placed into the Linux kernel *\${WORKDIR}* through your meta-layer. Explicitly set *KCONFIG\_MODE*:

```
KCONFIG_MODE = "alldefconfig"
```

### ***KERNEL\_ALT\_IMAGETYPE***

Specifies an alternate kernel image type for creation in addition to the kernel image type specified using the *KERNEL\_IMAGETYPE* and *KERNEL\_IMAGETYPES* variables.

### ***KERNEL\_ARTIFACT\_NAME***

Specifies the name of all of the build artifacts. You can change the name of the artifacts by changing the *KERNEL\_ARTIFACT\_NAME* variable.

The value of *KERNEL\_ARTIFACT\_NAME*, which is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file, has the following default value:

```
KERNEL_ARTIFACT_NAME ?= "${PKG}-${PKGVERSION}-${PKGNAME}${IMAGE_MACHINE_SUFFIX}${IMAGE_
→VERSION_SUFFIX}"
```

See the *PKG*, *PKGVERSION*, *PKGNAME*, *IMAGE\_MACHINE\_SUFFIX* and *IMAGE\_VERSION\_SUFFIX* variables for additional information.

### ***KERNEL\_CLASSES***

A list of classes defining kernel image types that the *kernel* class should inherit. You typically append this variable to enable extended image types. You can register custom kernel image types with the *kernel* class using this variable.

### ***KERNEL\_CONSOLE***

The *KERNEL\_CONSOLE* variable holds the value of the `console` parameter of the kernel command line and can be used in places such as a `wks` description file for *Wic images*.

The default value of this variable is extracted from the first console device and setting in *SERIAL\_CONSOLES*. If nothing is found in *SERIAL\_CONSOLES*, the default value is set to `ttys0,115200`.

For more information, see the [Kernel command-line documentation](#).

### ***KERNEL\_DANGLING\_FEATURES\_WARN\_ONLY***

When kernel configuration fragments are missing for some *KERNEL\_FEATURES* specified by layers or BSPs, building and configuring the kernel stops with an error.

You can turn these errors into warnings by setting the following in a *configuration file*:

```
KERNEL_DANGLING_FEATURES_WARN_ONLY = "1"
```

You will still be warned that runtime issues may occur, but at least the kernel configuration and build process will be allowed to continue.

### ***KERNEL\_DEBUG\_TIMESTAMPS***

If set to "1", enables timestamping functionality during building the kernel. The default is "0" to disable this for reproducibility reasons.

### ***KERNEL\_DEPLOY\_DEPEND***

Provides a means of controlling the dependency of an image recipe on the kernel. The default value is "virtual/kernel:do\_deploy", however for a small initramfs image or other images that do not need the kernel, this can be set to "" in the image recipe.

### ***KERNEL\_DEVICETREE***

Specifies the name of the generated Linux kernel device tree (i.e. the `.dtb`) file.

**i Nota**

There is legacy support for specifying the full path to the device tree. However, providing just the `.dtb` file is preferred.

In order to use this variable, the *kernel-devicetree* class must be inherited.

***KERNEL\_DEVICETREE\_BUNDLE***

When set to "1", this variable allows to bundle the Linux kernel and the Device Tree Binary together in a single file.

This feature is currently only supported on the "arm" (32 bit) architecture.

This variable is set to "0" by default by the *kernel-devicetree* class.

***KERNEL\_DTB\_LINK\_NAME***

The link name of the kernel device tree binary (DTB). This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
KERNEL_DTB_LINK_NAME ?= "${KERNEL_ARTIFACT_LINK_NAME}"
```

The value of the `KERNEL_ARTIFACT_LINK_NAME` variable, which is set in the same file, has the following value:

```
KERNEL_ARTIFACT_LINK_NAME ?= "${MACHINE}"
```

See the *MACHINE* variable for additional information.

***KERNEL\_DTB\_NAME***

The base name of the kernel device tree binary (DTB). This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
KERNEL_DTB_NAME ?= "${KERNEL_ARTIFACT_NAME}"
```

See *KERNEL\_ARTIFACT\_NAME* for additional information.

***KERNEL\_DTBDEST***

This variable, used by the *kernel-devicetree* class, allows to change the installation directory of the DTB (Device Tree Binary) files.

It is set by default to "\${KERNEL\_IMAGEDEST}" by the *kernel* class.

***KERNEL\_DTBVENDORED***

This variable, used by the *kernel-devicetree*, allows to ignore vendor subdirectories when installing DTB (Device Tree Binary) files, when it is set to "false".

To keep vendor subdirectories, set this variable to "true".

It is set by default to "false" by the *kernel* class.

### *KERNEL\_DTC\_FLAGS*

Specifies the `dtc` flags that are passed to the Linux kernel build system when generating the device trees (via `DTC_FLAGS` environment variable).

In order to use this variable, the *kernel-devicetree* class must be inherited.

### *KERNEL\_EXTRA\_ARGS*

Specifies additional `make` command-line arguments the OpenEmbedded build system passes on when compiling the kernel.

### *KERNEL\_FEATURES*

Includes additional kernel metadata. In the OpenEmbedded build system, the default Board Support Packages (BSPs) *Metadata* is provided through the *KMACHINE* and *KBRANCH* variables. You can use the *KERNEL\_FEATURES* variable from within the kernel recipe or kernel append file to further add metadata for all BSPs or specific BSPs.

The metadata you add through this variable includes config fragments and features descriptions, which usually includes patches as well as config fragments. You typically override the *KERNEL\_FEATURES* variable for a specific machine. In this way, you can provide validated, but optional, sets of kernel configurations and features.

For example, the following example from the `linux-yocto-rt_4.12` kernel recipe adds "netfilter" and "taskstats" features to all BSPs as well as "virtio" configurations to all QEMU machines. The last two statements add specific configurations to targeted machine types:

```
KERNEL_EXTRA_FEATURES ?= "features/netfilter/netfilter.scc features/taskstats/
↪taskstats.scc"
KERNEL_FEATURES:append = " ${KERNEL_EXTRA_FEATURES}"
KERNEL_FEATURES:append:qemuall = " cfg/virtio.scc"
KERNEL_FEATURES:append:qemux86 = " cfg/sound.scc cfg/paravirt_kvm.scc"
KERNEL_FEATURES:append:qemux86-64 = " cfg/sound.scc"
```

### *KERNEL\_FIT\_LINK\_NAME*

The link name of the kernel flattened image tree (FIT) image. This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
KERNEL_FIT_LINK_NAME ?= "${KERNEL_ARTIFACT_LINK_NAME}"
```

The value of the `KERNEL_ARTIFACT_LINK_NAME` variable, which is set in the same file, has the following value:

```
KERNEL_ARTIFACT_LINK_NAME ?= "${MACHINE}"
```

See the *MACHINE* variable for additional information.

### *KERNEL\_FIT\_NAME*

The base name of the kernel flattened image tree (FIT) image. This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
KERNEL_FIT_NAME ?= "${KERNEL_ARTIFACT_NAME}"
```



See [KERNEL\\_ARTIFACT\\_NAME](#) for additional information.

### ***KERNEL\_IMAGE\_LINK\_NAME***

The link name for the kernel image. This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
KERNEL_IMAGE_LINK_NAME ?= "${KERNEL_ARTIFACT_LINK_NAME}"
```

The value of the `KERNEL_ARTIFACT_LINK_NAME` variable, which is set in the same file, has the following value:

```
KERNEL_ARTIFACT_LINK_NAME ?= "${MACHINE}"
```

See the [MACHINE](#) variable for additional information.

### ***KERNEL\_IMAGE\_MAXSIZE***

Specifies the maximum allowable size of the kernel image file in kibibytes. If this variable is set, the sizes of all of the kernel image files listed in [KERNEL\\_IMAGETYPES](#) are checked against this value during the *do\_sizecheck* task. That task will warn about any of the kernel images that exceed the maximum, and will fail only if all images are too large.

[KERNEL\\_IMAGE\\_MAXSIZE](#) is useful for target devices that have a limited amount of space in which the kernel image must be stored.

By default, this variable is not set, which means the size of the kernel images are not checked.

### ***KERNEL\_IMAGE\_NAME***

The base name of the kernel image. This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
KERNEL_IMAGE_NAME ?= "${KERNEL_ARTIFACT_NAME}"
```

See [KERNEL\\_ARTIFACT\\_NAME](#) for additional information.

### ***KERNEL\_IMAGE\_STRIP\_EXTRA\_SECTIONS***

If this variable is set, it should contain the sections to be stripped from the `vmlinux` image by the kernel-related *do\_strip* task. As a simple example:

```
KERNEL_IMAGE_STRIP_EXTRA_SECTIONS = ".comment .note.* .debug"
```

### ***KERNEL\_IMAGETYPE***

The type of kernel to build for a device, usually set by the machine configuration files and defaults to "zImage". This variable is used when building the kernel and is passed to `make` as the target to build.

To build additional kernel image types, use [KERNEL\\_IMAGETYPES](#).

### ***KERNEL\_IMAGETYPES***

Lists additional types of kernel images to build for a device in addition to image type specified in [KERNEL\\_IMAGETYPE](#). Usually set by the machine configuration files.

### ***KERNEL\_LOCALVERSION***

This variable allows to append a string to the version of the kernel image. This corresponds to the `CONFIG_LOCALVERSION` kernel configuration parameter.

Using this variable is only useful when you are using a kernel recipe inheriting the *kernel* class, and which doesn't already set a local version. Therefore, setting this variable has no impact on `linux-yocto` kernels.

### ***KERNEL\_MODULE\_AUTOLOAD***

Lists kernel modules that need to be auto-loaded during boot.

#### ***i* Nota**

This variable replaces the deprecated *module\_autoload* variable.

You can use the *KERNEL\_MODULE\_AUTOLOAD* variable anywhere that it can be recognized by the kernel recipe or by an out-of-tree kernel module recipe (e.g. a machine configuration file, a distribution configuration file, an append file for the recipe, or the recipe itself).

Specify it as follows:

```
KERNEL_MODULE_AUTOLOAD += "module_name1 module_name2 module_name3"
```

Including *KERNEL\_MODULE\_AUTOLOAD* causes the OpenEmbedded build system to populate the `/etc/modules-load.d/modname.conf` file with the list of modules to be auto-loaded on boot. The modules appear one-per-line in the file. Here is an example of the most common use case:

```
KERNEL_MODULE_AUTOLOAD += "module_name"
```

For information on how to populate the `modname.conf` file with `modprobe.d` syntax lines, see the *KERNEL\_MODULE\_PROBECONF* variable.

### ***KERNEL\_MODULE\_INSTALL\_PREFIX***

When inheriting the *module* class, the *KERNEL\_MODULE\_INSTALL\_PREFIX* variable specifies the directory in which kernel modules are installed on target.

### ***KERNEL\_MODULE\_PROBECONF***

Provides a list of modules for which the OpenEmbedded build system expects to find `module_conf_modname` values that specify configuration for each of the modules. For information on how to provide those module configurations, see the *module\_conf\_\** variable.

### ***KERNEL\_PACKAGE\_NAME***

Specifies the base name of the kernel packages, such as "kernel" in the kernel packages such as "kernel-modules", "kernel-image" and "kernel-dbg".

The default value for this variable is set to "kernel" by the *kernel* class.

### ***KERNEL\_PATH***

The location of the kernel sources. This variable is set to the value of the *STAGING\_KERNEL\_DIR* within the *module* class. For information on how this variable is used, see the "*Incorporating Out-of-Tree Modules*" section in the Yocto Project Linux Kernel Development Manual.

To help maximize compatibility with out-of-tree drivers used to build modules, the OpenEmbedded build system also recognizes and uses the `KERNEL_SRC` variable, which is identical to the `KERNEL_PATH` variable. Both variables are common variables used by external Makefiles to point to the kernel source directory.

### `KERNEL_SPLIT_MODULES`

When inheriting the `kernel-module-split` class, this variable controls whether kernel modules are split into separate packages or bundled into a single package.

For some use cases, a monolithic kernel module package `KERNEL_PACKAGE_NAME` that contains all modules built from the kernel sources may be preferred to speed up the installation.

By default, this variable is set to 1, resulting in one package per module. Setting it to any other value will generate a single monolithic package containing all kernel modules.

#### Nota

If `KERNEL_SPLIT_MODULES` is set to 0, it is still possible to install all kernel modules at once by adding `kernel-modules` (assuming `KERNEL_PACKAGE_NAME` is `kernel-modules`) to `IMAGE_INSTALL`. The way it works is that a placeholder "kernel-modules" package will be created and will depend on every other individual kernel module packages.

### `KERNEL_SRC`

The location of the kernel sources. This variable is set to the value of the `STAGING_KERNEL_DIR` within the `module` class. For information on how this variable is used, see the "*Incorporating Out-of-Tree Modules*" section in the Yocto Project Linux Kernel Development Manual.

To help maximize compatibility with out-of-tree drivers used to build modules, the OpenEmbedded build system also recognizes and uses the `KERNEL_PATH` variable, which is identical to the `KERNEL_SRC` variable. Both variables are common variables used by external Makefiles to point to the kernel source directory.

### `KERNEL_STRIP`

Allows to specify which `strip` command to use to strip the kernel binary, typically either GNU binutils `strip` or `llvm-strip`.

### `KERNEL_TOOLCHAIN`

The `KERNEL_TOOLCHAIN` variable allows specifying the toolchain to use to build the Linux kernel. Its value can be one of the values supported by the `PREFERRED_TOOLCHAIN_TARGET` variable.

### `KERNEL_VERSION`

Specifies the version of the kernel as extracted from `version.h` or `utsrelease.h` within the kernel sources. Effects of setting this variable do not take effect until the kernel has been configured. Consequently, attempting to refer to this variable in contexts prior to configuration will not work.

### `KERNELDEPMODDEPEND`

Specifies whether the data referenced through `PKGDATA_DIR` is needed or not. `KERNELDEPMODDEPEND` does not control whether or not that data exists, but simply whether or not it is used. If you do not need to use the data, set the `KERNELDEPMODDEPEND` variable in your `Initramfs` recipe. Setting the variable there when the data is not needed avoids a potential dependency loop.

### *KFEATURE\_DESCRIPTION*

Provides a short description of a configuration fragment. You use this variable in the `.scc` file that describes a configuration fragment file. Here is the variable used in a file named `smp.scc` to describe SMP being enabled:

```
define KFEATURE_DESCRIPTION "Enable SMP"
```

### *KMACHINE*

The machine as known by the kernel. Sometimes the machine name used by the kernel does not match the machine name used by the OpenEmbedded build system. For example, the machine name that the OpenEmbedded build system understands as `core2-32-intel-common` goes by a different name in the Linux Yocto kernel. The kernel understands that machine as `intel-core2-32`. For cases like these, the *KMACHINE* variable maps the kernel machine name to the OpenEmbedded build system machine name.

These mappings between different names occur in the Yocto Linux Kernel's `meta` branch. As an example take a look in the `common/recipes-kernel/linux/linux-yocto_3.19.bbappend` file:

```
LINUX_VERSION:core2-32-intel-common = "3.19.0"
COMPATIBLE_MACHINE:core2-32-intel-common = "${MACHINE}"
SRCREV_meta:core2-32-intel-common = "8897ef68b30e7426bc1d39895e71fb155d694974"
SRCREV_machine:core2-32-intel-common =
→ "43b9eced9ba8a57add36af07736344dcc383f711"
KMACHINE:core2-32-intel-common = "intel-core2-32"
KBRANCH:core2-32-intel-common = "standard/base"
KERNEL_FEATURES:append:core2-32-intel-common = " ${KERNEL_FEATURES_INTEL_
→ COMMON}"
```

The *KMACHINE* statement says that the kernel understands the machine name as `"intel-core2-32"`. However, the OpenEmbedded build system understands the machine as `"core2-32-intel-common"`.

### *KMETA\_AUDIT*

When inheriting the *kernel-yocto* class, the *KMETA\_AUDIT* variable enables or disables auditing of Linux Kernel configuration. The default value for this variable is `"yes"`, and auditing is enabled. Set this variable to an empty string to disable auditing.

### *KMETA\_AUDIT\_WERROR*

When inheriting the *kernel-yocto* class and when the *KMETA\_AUDIT* and the *KMETA\_AUDIT\_WERROR* variables are set to non-empty strings, produce an error if Linux kernel configuration problems were detected, instead of warnings only. For more details on the Linux Kernel configuration auditing feature, see *KCONF\_AUDIT\_LEVEL* and *KCONF\_BSP\_AUDIT\_LEVEL*.

### *KMETA\_CONFIG\_FEATURES*

The *KMETA\_CONFIG\_FEATURES* variable defines features enabled for the *kernel-yocto* class. The following list of features are supported:

- `prefer-modules`: prefer a kernel configuration to be set as `m` instead of the default value `y` if the kernel configuration was defined as follows:

```
CONFIG_FOO=y # OVERRIDE:$MODULE_OR_Y
```

The default value of this variable is an empty string.

### ***KTYPE***

Defines the kernel type to be used in assembling the configuration. The linux-yocto recipes define "standard", "tiny", and "preempt-rt" kernel types. See the "[Kernel Types](#)" section in the Yocto Project Linux Kernel Development Manual for more information on kernel types.

You define the *KTYPE* variable in the [BSP Descriptions](#). The value you use must match the value used for the *LINUX\_KERNEL\_TYPE* value used by the kernel recipe.

### ***LABELS***

Provides a list of targets for automatic configuration.

See the *grub-efi* class for more information on how this variable is used.

### ***LAYERDEPENDS***

Lists the layers, separated by spaces, on which this layer depends. Optionally, you can specify a specific layer version for a dependency by adding it to the end of the layer name. Here is an example:

```
LAYERDEPENDS_mylayer = "anotherlayer (=3) "
```

In this previous example, version 3 of "anotherlayer" is compared against *LAYERVERSION\_anotherlayer*.

An error is produced if any dependency is missing or the version numbers (if specified) do not match exactly. This variable is used in the `conf/layer.conf` file and must be suffixed with the name of the specific layer (e.g. *LAYERDEPENDS\_mylayer*).

### ***LAYERDIR***

When used inside the `layer.conf` configuration file, this variable provides the path of the current layer. This variable is not available outside of `layer.conf` and references are expanded immediately when parsing of the file completes.

### ***LAYERDIR\_RE***

See *LAYERDIR\_RE* in the BitBake manual.

### ***LAYERRECOMMENDS***

Lists the layers, separated by spaces, recommended for use with this layer.

Optionally, you can specify a specific layer version for a recommendation by adding the version to the end of the layer name. Here is an example:

```
LAYERRECOMMENDS_mylayer = "anotherlayer (=3) "
```

In this previous example, version 3 of "anotherlayer" is compared against *LAYERVERSION\_anotherlayer*.

This variable is used in the `conf/layer.conf` file and must be suffixed with the name of the specific layer (e.g. *LAYERRECOMMENDS\_mylayer*).

### ***LAYERSERIES\_COMPAT***

See *LAYERSERIES\_COMPAT* in the BitBake manual.

### ***LAYERVERSION***

Optionally specifies the version of a layer as a single number. You can use this within *LAYERDEPENDS* for

another layer in order to depend on a specific version of the layer. This variable is used in the `conf/layer.conf` file and must be suffixed with the name of the specific layer (e.g. `LAYERVERSION_mylayer`).

## **LD**

The minimal command and arguments used to run the *linker*.

## **LDFLAGS**

Specifies the flags to pass to the linker. This variable is exported to an environment variable and thus made visible to the software being built during the compilation step.

Default initialization for *LDFLAGS* varies depending on what is being built:

- *TARGET\_LDFLAGS* when building for the target
- *BUILD\_LDFLAGS* when building for the build host (i.e. `-native`)
- *BUILDSDK\_LDFLAGS* when building for an SDK (i.e. `nativesdk-`)

## **LEAD\_SONAME**

Specifies the lead (or primary) compiled library file (i.e. `.so`) that the *debian* class applies its naming policy to given a recipe that packages multiple libraries.

This variable works in conjunction with the *debian* class.

## **LIC\_FILES\_CHKSUM**

Checksums of the license text in the recipe source code.

This variable tracks changes in license text of the source code files. If the license text is changed, it will trigger a build failure, which gives the developer an opportunity to review any license change.

This variable must be defined for all recipes (unless *LICENSE* is set to "CLOSED").

For more information, see the "*Tracking License Changes*" section in the Yocto Project Development Tasks Manual.

## **LICENSE**

This is a required field in an OpenEmbedded recipe file, and should contain a *SPDX License Expression* that describes the source license(s) for the recipe. Keep in mind a few rules:

- Separate license name using `OR` when there is a choice between licenses
- Separate license names using `AND` when multiple licenses apply to different parts of the source code
- All licenses must be valid *SPDX License Identifiers*
- Any License that does not come from the *SPDX License List* must be prefixed with `LicenseRef-`.

Here are some examples:

```
LICENSE = "LGPL-2.1-only OR GPL-3.0-only"
LICENSE = "MPL-1.0 AND LGPL-2.1-only"
LICENSE = "GPL-2.0-or-later"
```

The first example is from the recipes for Qt, which the user may choose to distribute under either the LGPL version 2.1 or GPL version 3. The second example is from Cairo where two licenses cover different parts of the source code. The final example is from `sysstat`, which presents a single license.

You can also specify licenses on a per-package basis to handle situations where components of the output have different licenses. For example, a piece of software whose code is licensed under GPLv2 but has accompanying documentation licensed under the GNU Free Documentation License 1.2 could be specified as follows:

```
LICENSE = "GFDL-1.2 AND GPL-2.0-only"
LICENSE:${PN} = "GPL-2.0-only"
LICENSE:${PN}-doc = "GFDL-1.2"
```

#### Nota

A recipe's *LICENSE* value must be accompanied by an associated *LIC\_FILES\_CHKSUM* value.

### *LICENSE\_CREATE\_PACKAGE*

Setting *LICENSE\_CREATE\_PACKAGE* to "1" causes the OpenEmbedded build system to create an extra package (i.e. *\${PN}-lic*) for each recipe and to add those packages to the *RRECOMMENDS*:*\${PN}*.

The *\${PN}-lic* package installs a directory in */usr/share/licenses* named *\${PN}*, which is the recipe's base name, and installs files in that directory that contain license and copyright information (i.e. copies of the appropriate license files from *meta/common-licenses* that match the licenses specified in the *LICENSE* variable of the recipe metadata and copies of files marked in *LIC\_FILES\_CHKSUM* as containing license text).

For related information on providing license text, see the *COPY\_LIC\_DIRS* variable, the *COPY\_LIC\_MANIFEST* variable, and the "Providing License Text" section in the Yocto Project Development Tasks Manual.

### *LICENSE\_FLAGS*

Specifies additional flags for a recipe you must allow through *LICENSE\_FLAGS\_ACCEPTED* in order for the recipe to be built. When providing multiple flags, separate them with spaces.

This value is independent of *LICENSE* and is typically used to mark recipes that might require additional licenses in order to be used in a commercial product. For more information, see the "Enabling Commercially Licensed Recipes" section in the Yocto Project Development Tasks Manual.

### *LICENSE\_FLAGS\_ACCEPTED*

Lists license flags that when specified in *LICENSE\_FLAGS* within a recipe should not prevent that recipe from being built. For more information, see the "Enabling Commercially Licensed Recipes" section in the Yocto Project Development Tasks Manual.

### *LICENSE\_FLAGS\_DETAILS*

Adds details about a flag in *LICENSE\_FLAGS*. This way, if such a flag is not accepted through *LICENSE\_FLAGS\_ACCEPTED*, the error message will be more informative, containing the specified extra details.

For example, a recipe with an EULA may set:

```
LICENSE_FLAGS = "FooBar-EULA"
LICENSE_FLAGS_DETAILS[FooBar-EULA] = "For further details, see https://example.
↪com/eula."
```

If `FooBar-EULA` isn't in `LICENSE_FLAGS_ACCEPTED`, the error message is more useful:

```
Has a restricted license 'FooBar-EULA' which is not listed in your LICENSE_
↪FLAGS_ACCEPTED.
For further details, see https://example.com/eula.
```

### ***LICENSE\_PATH***

Path to additional licenses used during the build. By default, the OpenEmbedded build system uses `COMMON_LICENSE_DIR` to define the directory that holds common license text used during the build. The `LICENSE_PATH` variable allows you to extend that location to other areas that have additional licenses:

```
LICENSE_PATH += "path-to-additional-common-licenses"
```

### ***LINUX\_KERNEL\_TYPE***

Defines the kernel type to be used in assembling the configuration. The linux-yocto recipes define "standard", "tiny", and "preempt-rt" kernel types. See the "*Kernel Types*" section in the Yocto Project Linux Kernel Development Manual for more information on kernel types.

If you do not specify a `LINUX_KERNEL_TYPE`, it defaults to "standard". Together with `KMACHINE`, the `LINUX_KERNEL_TYPE` variable defines the search arguments used by the kernel tools to find the appropriate description within the kernel *Metadata* with which to build out the sources and configuration.

### ***LINUX\_VERSION***

The Linux version from `kernel.org` on which the Linux kernel image being built using the OpenEmbedded build system is based. You define this variable in the kernel recipe. For example, the `linux-yocto-3.4.bb` kernel recipe found in `meta/recipes-kernel/linux` defines the variables as follows:

```
LINUX_VERSION ?= "3.4.24"
```

The `LINUX_VERSION` variable is used to define `PV` for the recipe:

```
PV = "${LINUX_VERSION}+git"
```

### ***LINUX\_VERSION\_EXTENSION***

A string extension compiled into the version string of the Linux kernel built with the OpenEmbedded build system. You define this variable in the kernel recipe. For example, the linux-yocto kernel recipes all define the variable as follows:

```
LINUX_VERSION_EXTENSION ?= "-yocto-${LINUX_KERNEL_TYPE}"
```

Defining this variable essentially sets the Linux kernel configuration item `CONFIG_LOCALVERSION`, which is visible through the `uname` command. Here is an example that shows the extension assuming it was set as previously shown:

```
$ uname -r
3.7.0-rc8-custom
```



## LOCALE\_PATHS

The `LOCALE_PATHS` variable holds a whitespace separated list of paths that are scanned to construct `-locale` packages during *Suddivisione in Pacchetti*. The list contains `${datadir}/locale` by default.

## LOCALE\_UTF8\_IS\_DEFAULT

If set, locale names are renamed such that those lacking an explicit encoding (e.g. `en_US`) will always be UTF-8, and non-UTF-8 encodings are renamed to, e.g., `en_US.ISO-8859-1`. Otherwise, the encoding is specified by *Glibc*'s `SUPPORTED` file. This is not supported for pre-compiled locales.

## LOG\_DIR

Specifies the directory to which the OpenEmbedded build system writes overall log files. The default directory is `${TMPDIR}/log`.

For the directory containing logs specific to each task, see the `T` variable.

## LTO

The `LTO` variable defines the flags specific to the `lto` *distro feature*. The value of this variable is appended to the `TARGET_LDFLAGS` variable, adding *Link-Time Optimisation* flags to the linker in-use.

## MACHINE

Specifies the target device for which the image is built. You can define the `MACHINE` in two ways:

- with the *machine/* fragment:

```
$ bitbake-config-build enable-fragment machine/<MACHINE>
```

Replace `<MACHINE>` with the name of the machine in the above command.

- in the *build/conf/local.conf* file found in the *Build Directory*.

The variable corresponds to a machine configuration file of the same name, through which machine-specific configurations are set. Thus, when `MACHINE` is set to `"qemux86"`, the corresponding `qemux86.conf` machine configuration file can be found in *OpenEmbedded-Core (OE-Core)* in `meta/conf/machine`.

The list of machines supported by the Yocto Project as shipped include the following:

```
MACHINE ?= "qemuarm"
MACHINE ?= "qemuarm64"
MACHINE ?= "qemumips"
MACHINE ?= "qemumips64"
MACHINE ?= "qemuppc"
MACHINE ?= "qemux86"
MACHINE ?= "qemux86-64"
MACHINE ?= "genericx86"
MACHINE ?= "genericx86-64"
MACHINE ?= "beaglebone"
```

The last five are Yocto Project reference hardware boards, which are provided in the `meta-yocto-bsp` layer.

**i Nota**

Adding additional Board Support Package (BSP) layers to your configuration adds new possible settings for *MACHINE*.

***MACHINE\_ARCH***

Specifies the name of the machine-specific architecture. This variable is set automatically from *MACHINE* or *TUNE\_PKGARCH*. You should not hand-edit the *MACHINE\_ARCH* variable.

***MACHINE\_ESSENTIAL\_EXTRA\_RDEPENDS***

A list of required machine-specific packages to install as part of the image being built. The build process depends on these packages being present. Furthermore, because this is a "machine-essential" variable, the list of packages are essential for the machine to boot. The impact of this variable affects images based on `packagegroup-core-boot`, including the `core-image-minimal` image.

This variable is similar to the *MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS* variable with the exception that the image being built has a build dependency on the variable's list of packages. In other words, the image will not build if a file in this list is not found.

As an example, suppose the machine for which you are building requires `example-init` to be run during boot to initialize the hardware. In this case, you would use the following in the machine's `.conf` configuration file:

```
MACHINE_ESSENTIAL_EXTRA_RDEPENDS += "example-init"
```

***MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS***

A list of recommended machine-specific packages to install as part of the image being built. The build process does not depend on these packages being present. However, because this is a "machine-essential" variable, the list of packages are essential for the machine to boot. The impact of this variable affects images based on `packagegroup-core-boot`, including the `core-image-minimal` image.

This variable is similar to the *MACHINE\_ESSENTIAL\_EXTRA\_RDEPENDS* variable with the exception that the image being built does not have a build dependency on the variable's list of packages. In other words, the image will still build if a package in this list is not found. Typically, this variable is used to handle essential kernel modules, whose functionality may be selected to be built into the kernel rather than as a module, in which case a package will not be produced.

Consider an example where you have a custom kernel where a specific touchscreen driver is required for the machine to be usable. However, the driver can be built as a module or into the kernel depending on the kernel configuration. If the driver is built as a module, you want it to be installed. But, when the driver is built into the kernel, you still want the build to succeed. This variable sets up a "recommends" relationship so that in the latter case, the build will not fail due to the missing package. To accomplish this, assuming the package for the module was called `kernel-module-ab123`, you would use the following in the machine's `.conf` configuration file:

```
MACHINE_ESSENTIAL_EXTRA_RRECOMMENDS += "kernel-module-ab123"
```

**i Nota**

In this example, the `kernel-module-ab123` recipe needs to explicitly set its `PACKAGES` variable to ensure that BitBake does not use the kernel recipe's `PACKAGES_DYNAMIC` variable to satisfy the dependency.

Some examples of these machine essentials are flash, screen, keyboard, mouse, or touchscreen drivers (depending on the machine).

***MACHINE\_EXTRA\_RDEPENDS***

A list of machine-specific packages to install as part of the image being built that are not essential for the machine to boot. However, the build process for more fully-featured images depends on the packages being present.

This variable affects all images based on `packagegroup-base`, which does not include the `core-image-minimal` or `core-image-full-cmdline` images.

The variable is similar to the `MACHINE_EXTRA_RRECOMMENDS` variable with the exception that the image being built has a build dependency on the variable's list of packages. In other words, the image will not build if a file in this list is not found.

An example is a machine that has WiFi capability but is not essential for the machine to boot the image. However, if you are building a more fully-featured image, you want to enable the WiFi. The package containing the firmware for the WiFi hardware is always expected to exist, so it is acceptable for the build process to depend upon finding the package. In this case, assuming the package for the firmware was called `wifidriver-firmware`, you would use the following in the `.conf` file for the machine:

```
MACHINE_EXTRA_RDEPENDS += "wifidriver-firmware"
```

***MACHINE\_EXTRA\_RRECOMMENDS***

A list of machine-specific packages to install as part of the image being built that are not essential for booting the machine. The image being built has no build dependency on this list of packages.

This variable affects only images based on `packagegroup-base`, which does not include the `core-image-minimal` or `core-image-full-cmdline` images.

This variable is similar to the `MACHINE_EXTRA_RDEPENDS` variable with the exception that the image being built does not have a build dependency on the variable's list of packages. In other words, the image will build if a file in this list is not found.

An example is a machine that has WiFi capability but is not essential For the machine to boot the image. However, if you are building a more fully-featured image, you want to enable WiFi. In this case, the package containing the WiFi kernel module will not be produced if the WiFi driver is built into the kernel, in which case you still want the build to succeed instead of failing as a result of the package not being found. To accomplish this, assuming the package for the module was called `kernel-module-examplewifi`, you would use the following in the `.conf` file for the machine:

```
MACHINE_EXTRA_RRECOMMENDS += "kernel-module-examplewifi"
```

### *MACHINE\_FEATURES*

Specifies the list of hardware features the *MACHINE* is capable of supporting. For related information on enabling features, see the *DISTRO\_FEATURES*, *COMBINED\_FEATURES*, and *IMAGE\_FEATURES* variables.

For a list of hardware features supported by the Yocto Project as shipped, see the "*Machine Features*" section.

### *MACHINE\_FEATURES\_DEFAULTS*

Specifies a space-separated list of default machine features provided by the *OpenEmbedded Build System*. This list should not be modified directly, but instead *MACHINE\_FEATURES\_OPTED\_OUT* should be used to prevent default machine features from being enabled.

See *Default Features* for more information.

### *MACHINE\_FEATURES\_OPTED\_OUT*

Specifies a space-separated list of machine features to opt out from when they are provided by the *MACHINE\_FEATURES\_DEFAULTS* variable.

You can also opt out of all default features by setting *MACHINE\_FEATURES\_OPTED\_OUT* to `*`:

```
MACHINE_FEATURES_OPTED_OUT = "*" 
```

See *Default Features* for more information.

### *MACHINEOVERRIDES*

A colon-separated list of overrides that apply to the current machine. By default, this list includes the value of *MACHINE*.

You can extend *MACHINEOVERRIDES* to add extra overrides that should apply to a machine. For example, all machines emulated in QEMU (e.g. `qemuarm`, `qemux86`, and so forth) include a file named `meta/conf/machine/include/qemu.inc` that prepends the following override to *MACHINEOVERRIDES*:

```
MACHINEOVERRIDES =. "qemuall:" 
```

This override allows variables to be overridden for all machines emulated in QEMU, like in the following example from the `connman-conf` recipe:

```
SRC_URI:append:qemuall = " file://wired.config \
    file://wired-setup \
    "
```

The underlying mechanism behind *MACHINEOVERRIDES* is simply that it is included in the default value of *OVERRIDES*.

### *MAINTAINER*

The email address of the distribution maintainer.

### *MESON\_BUILDTYPE*

Value of the Meson `--buildtype` argument used by the *meson* class. It defaults to `debug` if *DEBUG\_BUILD* is set to `"1"`, and `plain` otherwise.

See [Meson build options](#) for the values you could set in a recipe. Values such as `plain`, `debug`, `debugoptimized`, `release` and `minsize` allow you to specify the inclusion of debugging symbols and the compiler optimizations (none, performance or size).

### **MESON\_INSTALL\_TAGS**

A variable for the *meson* class, allowing to specify install tags (`--tags` argument of the `meson install` command).

### **MESON\_TARGET**

A variable for the *meson* class, allowing to choose a Meson target to build in *do\_compile*. Otherwise, the default targets are built.

### **METADATA\_BRANCH**

The branch currently checked out for the OpenEmbedded-Core layer (path determined by *COREBASE*).

### **METADATA\_REVISION**

The revision currently checked out for the OpenEmbedded-Core layer (path determined by *COREBASE*).

### **MIME\_XDG\_PACKAGES**

The current implementation of the *mime-xdg* class cannot detect `.desktop` files installed through absolute symbolic links. Use this setting to make the class create post-install and post-remove scripts for these packages anyway, to invoke the `update-desktop-database` command.

### **MIRRORS**

Specifies additional paths from which the OpenEmbedded build system gets source code. When the build system searches for source code, it first tries the local download directory. If that location fails, the build system tries locations defined by *PREMIRRORS*, the upstream source, and then locations specified by *MIRRORS* in that order.

The default value for *MIRRORS* is defined in the `meta/classes-global/mirrors.bbclass` file in the core metadata layer.

See the definition of this variable in the BitBake Manual for more details: [MIRRORS](#).

### **MLPREFIX**

Specifies a prefix has been added to *PN* to create a special version of a recipe or package (i.e. a Multilib version). The variable is used in places where the prefix needs to be added to or removed from a name (e.g. the *BPN* variable). *MLPREFIX* gets set when a prefix has been added to *PN*.

#### **Nota**

The "ML" in *MLPREFIX* stands for "MultiLib". This representation is historical and comes from a time when "*nativesdk*" was a suffix rather than a prefix on the recipe name. When "*nativesdk*" was turned into a prefix, it made sense to set *MLPREFIX* for it as well.

To help understand when *MLPREFIX* might be needed, consider when *BBCLASSEXTEND* is used to provide a *nativesdk* version of a recipe in addition to the target version. If that recipe declares build-time dependencies on tasks in other recipes by using *DEPENDS*, then a dependency on "foo" will automatically get rewritten to a dependency on "nativesdk-foo". However, dependencies like the following will not get rewritten automatically:

```
do_foo[depends] += "recipe:do_foo"
```

If you want such a dependency to also get transformed, you can do the following:

```
do_foo[depends] += "${MLPREFIX}recipe:do_foo"
```

### *module\_autoload*

This variable has been replaced by the *KERNEL\_MODULE\_AUTOLOAD* variable. You should replace all occurrences of *module\_autoload* with additions to *KERNEL\_MODULE\_AUTOLOAD*, for example:

```
module_autoload_rfcomm = "rfcomm"
```

should now be replaced with:

```
KERNEL_MODULE_AUTOLOAD += "rfcomm"
```

See the *KERNEL\_MODULE\_AUTOLOAD* variable for more information.

### *module\_conf*

Specifies *modprobe.d(5)* syntax lines for inclusion in the */etc/modprobe.d/modname.conf* file.

You can use this variable anywhere that it can be recognized by the kernel recipe or out-of-tree kernel module recipe (e.g. a machine configuration file, a distribution configuration file, an append file for the recipe, or the recipe itself). If you use this variable, you must also be sure to list the module name in the *KERNEL\_MODULE\_PROBECONF* variable.

Here is the general syntax:

```
module_conf_module_name = "modprobe.d-syntax"
```

You must use the kernel module name override.

Run `man modprobe.d` in the shell to find out more information on the exact syntax you want to provide with *module\_conf*.

Including *module\_conf* causes the OpenEmbedded build system to populate the */etc/modprobe.d/modname.conf* file with *modprobe.d* syntax lines. Here is an example that adds the options *arg1* and *arg2* to a module named *mymodule*:

```
module_conf_mymodule = "options mymodule arg1=val1 arg2=val2"
```

For information on how to specify kernel modules to auto-load on boot, see the *KERNEL\_MODULE\_AUTOLOAD* variable.

### *MODULE\_TARBALL\_DEPLOY*

Controls creation of the *modules-\*.tgz* file. Set this variable to "0" to disable creation of this file, which contains all of the kernel modules resulting from a kernel build.

### *MODULE\_TARBALL\_LINK\_NAME*

The link name of the kernel module tarball. This variable is set in the *meta/classes-recipe/kernel-artifact-names.bbclass* file as follows:

```
MODULE_TARBALL_LINK_NAME ?= "${KERNEL_ARTIFACT_LINK_NAME}"
```

The value of the `KERNEL_ARTIFACT_LINK_NAME` variable, which is set in the same file, has the following value:

```
KERNEL_ARTIFACT_LINK_NAME ?= "${MACHINE}"
```

See the *MACHINE* variable for additional information.

### MODULE\_TARBALL\_NAME

The base name of the kernel module tarball. This variable is set in the `meta/classes-recipe/kernel-artifact-names.bbclass` file as follows:

```
MODULE_TARBALL_NAME ?= "${KERNEL_ARTIFACT_NAME}"
```

See *KERNEL\_ARTIFACT\_NAME* for additional information.

### MOUNT\_BASE

On non-systemd systems (where `udev-extraconf` is being used), specifies the base directory for auto-mounting filesystems. The default value is `"/run/media"`.

### MOUNT\_GROUP

On non-systemd systems (where `udev-extraconf` is being used), specifies the mount group for auto-mounting filesystems. The default value is `"disk"`.

### MULTIMACH\_TARGET\_SYS

Uniquely identifies the type of the target system for which packages are being built. This variable allows output for different types of target systems to be put into different subdirectories of the same output directory.

The default value of this variable is:

```
${PACKAGE_ARCH}${TARGET_VENDOR}-${TARGET_OS}
```

Some classes (e.g. *cross-canadian*) modify the *MULTIMACH\_TARGET\_SYS* value.

See the *STAMP* variable for an example. See the *STAGING\_DIR\_TARGET* variable for more information.

### NATIVESBSTRING

A string identifying the host distribution. Strings consist of the host distributor ID followed by the release, as reported by the `lsb_release` tool or as read from `/etc/lsb-release`. For example, when running a build on Ubuntu 12.10, the value is `"Ubuntu-12.10"`. If this information is unable to be determined, the value resolves to `"Unknown"`.

This variable is used by default to isolate native shared state packages for different distributions (e.g. to avoid problems with `glibc` version incompatibilities). Additionally, the variable is checked against *SANITY\_TESTED\_DISTROS* if that variable is set.

### NM

The minimal command and arguments to run *nm*.

### NO\_GENERIC\_LICENSE

Avoids QA errors when you use a non-common, non-CLOSED license in a recipe. There are packages, such

as the `linux-firmware` package, with many licenses that are not in any way common. Also, new licenses are added occasionally to avoid introducing a lot of common license files, which are only applicable to a specific package. `NO_GENERIC_LICENSE` is used to allow copying a license that does not exist in common licenses.

The following example shows how to add `NO_GENERIC_LICENSE` to a recipe:

```
NO_GENERIC_LICENSE[license_name] = "license_file_in_fetched_source"
```

Here is an example that uses the `LICENSE.Abilis.txt` file as the license from the fetched source:

```
NO_GENERIC_LICENSE[Firmware-Abilis] = "LICENSE.Abilis.txt"
```

## `NO_RECOMMENDATIONS`

Prevents installation of all "recommended-only" packages. Recommended-only packages are packages installed only through the `RRECOMMENDS` variable). Setting the `NO_RECOMMENDATIONS` variable to "1" turns this feature on:

```
NO_RECOMMENDATIONS = "1"
```

You can set this variable globally in a *configuration file* or you can specify it in an image recipe directly:

```
NO_RECOMMENDATIONS = "1"
```

It is important to realize that if you choose to not install packages using this variable and some other packages are dependent on them (i.e. listed in a recipe's `RDEPENDS` variable), the OpenEmbedded build system ignores your request and will install the packages to avoid dependency errors.

### Nota

Some recommended packages might be required for certain system functionality, such as kernel modules. It is up to you to add packages with the `IMAGE_INSTALL` variable.

This variable is supported for all packaging backends.

See the `BAD_RECOMMENDATIONS` and the `PACKAGE_EXCLUDE` variables for related information.

## `NOAUTOPACKAGEDEBUG`

Disables auto package from splitting `.debug` files. If a recipe requires `FILES:${PN}-dbg` to be set manually, the `NOAUTOPACKAGEDEBUG` can be defined allowing you to define the content of the debug package. For example:

```
NOAUTOPACKAGEDEBUG = "1"
FILES:${PN}-dev = "${includedir}/${QT_DIR_NAME}/Qt/*"
FILES:${PN}-dbg = "/usr/src/debug/"
FILES:${QT_BASE_NAME}-demos-doc = "${docdir}/${QT_DIR_NAME}/qch/qt.qch"
```

## `NON_MULTILIB_RECIPES`

A list of recipes that should not be built for multilib. OE-Core's `multilib.conf` file defines a reasonable starting point for this list with:



```
NON_MULTILIB_RECIPES = "grub grub-efi make-mod-scripts ovmf u-boot"
```

**OBJCOPY**

The minimal command and arguments to run *objcopy*.

**OBJDUMP**

The minimal command and arguments to run *objdump*.

**OE\_BINCONFIG\_EXTRA\_MANGLE**

When inheriting the *binconfig* class, this variable specifies additional arguments passed to the "sed" command. The sed command alters any paths in configuration scripts that have been set up during compilation. Inheriting this class results in all paths in these scripts being changed to point into the `sysroots/` directory so that all builds that use the script will use the correct directories for the cross compiling layout.

See the `meta/classes-recipe/binconfig.bbclass` in *OpenEmbedded-Core (OE-Core)* for details on how this class applies these additional sed command arguments.

**OE\_FRAGMENTS**

The *OE\_FRAGMENTS* variable holds the list of *Configuration Fragments* currently enabled for the build. For details on how to use fragments, see the *Using Configuration Fragments* section of the Yocto Project Reference Manual.

**OE\_FRAGMENTS\_BUILTIN**

The *OE\_FRAGMENTS\_BUILTIN* variable holds the list of *Built-in Fragments* available for being set with `bitbake-config-build`. For details on how to use fragments, see the *Using Configuration Fragments* section of the Yocto Project Reference Manual.

**OE\_FRAGMENTS\_METADATA\_VARS**

The *OE\_FRAGMENTS\_METADATA\_VARS* variable holds the list of variables that are required to set in a standard *Configuration Fragment* file. In *OpenEmbedded-Core (OE-Core)*, these variables are *BB\_CONF\_FRAGMENT\_SUMMARY* and *BB\_CONF\_FRAGMENT\_DESCRIPTION*.

**OE\_FRAGMENTS\_PREFIX**

The *OE\_FRAGMENTS\_PREFIX* variable defines the prefix where *BitBake* tries to locate *Configuration Fragments* in *layers*. For details on how to use fragments, see the *Using Configuration Fragments* section of the Yocto Project Reference Manual.

**OE\_INIT\_ENV\_SCRIPT**

The name of the build environment setup script for the purposes of setting up the environment within the extensible SDK. The default value is "oe-init-build-env".

If you use a custom script to set up your build environment, set the *OE\_INIT\_ENV\_SCRIPT* variable to its name.

**OE\_SHARED\_UMASK**

The *OE\_SHARED\_UMASK* variable contains the *umask* definition for shared files (for example files in *SSTATE\_DIR* or *DL\_DIR*).

**OE\_TERMINAL**

Controls how the OpenEmbedded build system spawns interactive terminals on the host development system

(e.g. using the BitBake command with the `-c devshell` command-line option). For more information, see the "[Using a Development Shell](#)" section in the Yocto Project Development Tasks Manual.

You can use the following values for the `OE_TERMINAL` variable:

- auto
- gnome
- xfce
- rxvt
- screen
- konsole
- none

### **`OE_CMAKE_GENERATOR`**

A variable for the `cmake` class, allowing to choose which back-end will be generated by CMake to build an application.

By default, this variable is set to `Ninja`, which is faster than GNU make, but if building is broken with Ninja, a recipe can use this variable to use GNU make instead:

```
OE_CMAKE_GENERATOR = "Unix Makefiles"
```

### **`OEQA_REPRODUCIBLE_TEST_LEAF_TARGETS`**

Set build target(s) for build reproducibility testing but activate *shared state* build for most dependencies (i.e. the ones explicitly listed in `DEPENDS`, which may not be all dependencies, c.f. `[depends] varflags`, `PACKAGE_DEPENDS` and other implementations). See [Reproducible Builds](#).

### **`OEQA_REPRODUCIBLE_TEST_PACKAGE`**

Set the package manager(s) for build reproducibility testing. See [reproducible.py](#) and [Reproducible Builds](#).

### **`OEQA_REPRODUCIBLE_TEST_SSTATE_TARGETS`**

Set build targets which can be rebuilt using *shared state* when running build reproducibility tests. See [Reproducible Builds](#).

### **`OEQA_REPRODUCIBLE_TEST_TARGET`**

Set build target for build reproducibility testing. By default all available recipes are compiled with "bitbake world", see also [EXCLUDE\\_FROM\\_WORLD](#) and [Reproducible Builds](#).

### **`OEROOT`**

The directory from which the top-level build environment setup script is sourced. The Yocto Project provides a top-level build environment setup script: `oe-init-build-env`. When you run this script, the `OEROOT` variable resolves to the directory that contains the script.

For additional information on how this variable is used, see the initialization script.

### **`OLDEST_KERNEL`**

Declares the oldest version of the Linux kernel that the produced binaries must support. This variable is passed into the build of the Embedded GNU C Library (`glibc`).

The default for this variable comes from the `meta/conf/bitbake.conf` configuration file. You can override this default by setting the variable in a custom distribution configuration file.

#### ***OPENSSSH\_HOST\_KEY\_DIR***

Specifies the directory where OpenSSH host keys are stored. Default is `/etc/ssh`.

#### ***OPENSSSH\_HOST\_KEY\_DIR\_READONLY\_CONFIG***

Specifies the directory where OpenSSH host keys are stored when the device uses a read-only filesystem. Default is `/var/run/ssh`.

#### ***OPKG\_MAKE\_INDEX\_EXTRA\_PARAMS***

Specifies extra parameters for the `opkg-make-index` command.

#### ***OPKGBUILDCMD***

The variable *OPKGBUILDCMD* specifies the command used to build `opkg` packages when using the *package\_ipk* class. It is defined in *package\_ipk* as:

```
OPKGBUILDCMD ??= 'opkg-build -Z zstd -a "${ZSTD_DEFAULTS}''
```

#### ***OVERLAYFS\_ETC\_DEVICE***

When the *overlayfs-etc* class is inherited, specifies the device to be mounted for the read/write layer of `/etc`. There is no default, so you must set this if you wish to enable *overlayfs-etc*, for example, assuming `/dev/mmcblk0p2` was the desired device:

```
OVERLAYFS_ETC_DEVICE = "/dev/mmcblk0p2"
```

#### ***OVERLAYFS\_ETC\_EXPOSE\_LOWER***

When the *overlayfs-etc* class is inherited, if set to `"1"` then a read-only access to the original `/etc` content will be provided as a `lower/` subdirectory of *OVERLAYFS\_ETC\_MOUNT\_POINT*. The default value is `"0"`.

#### ***OVERLAYFS\_ETC\_FSTYPE***

When the *overlayfs-etc* class is inherited, specifies the file system type for the read/write layer of `/etc`. There is no default, so you must set this if you wish to enable *overlayfs-etc*, for example, assuming the file system is `ext4`:

```
OVERLAYFS_ETC_FSTYPE = "ext4"
```

#### ***OVERLAYFS\_ETC\_MOUNT\_OPTIONS***

When the *overlayfs-etc* class is inherited, specifies the mount options for the read-write layer. The default value is `"defaults"`.

#### ***OVERLAYFS\_ETC\_MOUNT\_POINT***

When the *overlayfs-etc* class is inherited, specifies the parent mount path for the filesystem layers. There is no default, so you must set this if you wish to enable *overlayfs-etc*, for example if the desired path is `"/data"`:

```
OVERLAYFS_ETC_MOUNT_POINT = "/data"
```

#### ***OVERLAYFS\_ETC\_USE\_ORIG\_INIT\_NAME***

When the *overlayfs-etc* class is inherited, controls how the generated init will be named. For more information, see the *overlayfs-etc* class documentation. The default value is `"1"`.

### *OVERLAYFS\_MOUNT\_POINT*

When inheriting the *overlayfs* class, specifies mount point(s) to be used. For example:

```
OVERLAYFS_MOUNT_POINT[data] = "/data"
```

The assumes you have a `data.mount` systemd unit defined elsewhere in your BSP (e.g. in `systemd-machine-units` recipe) and it is installed into the image. For more information see *overlayfs*.

#### **Nota**

Although the *overlayfs* class is inherited by individual recipes, *OVERLAYFS\_MOUNT\_POINT* should be set in your machine configuration.

### *OVERLAYFS\_QA\_SKIP*

When inheriting the *overlayfs* class, provides the ability to disable QA checks for particular overlayfs mounts. For example:

```
OVERLAYFS_QA_SKIP[data] = "mount-configured"
```

#### **Nota**

Although the *overlayfs* class is inherited by individual recipes, *OVERLAYFS\_QA\_SKIP* should be set in your machine configuration.

### *OVERLAYFS\_WRITABLE\_PATHS*

When inheriting the *overlayfs* class, specifies writable paths used at runtime for the recipe. For example:

```
OVERLAYFS_WRITABLE_PATHS[data] = "/usr/share/my-custom-application"
```

### *OVERRIDES*

A colon-separated list of overrides that currently apply. Overrides are a BitBake mechanism that allows variables to be selectively overridden at the end of parsing. The set of overrides in *OVERRIDES* represents the "state" during building, which includes the current recipe being built, the machine for which it is being built, and so forth.

As an example, if the string "an-override" appears as an element in the colon-separated list in *OVERRIDES*, then the following assignment will override `FOO` with the value "overridden" at the end of parsing:

```
FOO:an-override = "overridden"
```

See the "Conditional Syntax (Overrides)" section in the BitBake User Manual for more information on the overrides mechanism.

The default value of *OVERRIDES* includes the values of the *CLASSOVERRIDE*, *MACHINEOVERRIDES*, and *DISTROOVERRIDES* variables. Another important override included by default is `pn-${PN}`. This override allows variables to be set for a single recipe within configuration (`.conf`) files. Here is an example:

```
FOO:pn-myrecipe = "myrecipe-specific value"
```

#### **Nota**

An easy way to see what overrides apply is to run the command `bitbake-getvar -r myrecipe OVERRIDES`. See the "[Viewing Variable Values](#)" section in the Yocto Project Development Tasks Manual for more information.

## **P**

The recipe name and version. *P* is comprised of the following:

```
${PN}-${PV}
```

## **P4DIR**

See [P4DIR](#) in the BitBake manual.

## **PACKAGE\_ADD\_METADATA**

This variable defines additional metadata to add to packages.

You may find you need to inject additional metadata into packages. This variable allows you to do that by setting the injected data as the value. Multiple fields can be added by splitting the content with the literal separator `"n"`.

The suffixes `'_IPK'`, `'_DEB'`, or `'_RPM'` can be applied to the variable to do package type specific settings. It can also be made package specific by using the package name as a suffix.

You can find out more about applying this variable in the "[Adding custom metadata to packages](#)" section in the Yocto Project Development Tasks Manual.

## **PACKAGE\_ARCH**

The architecture of the resulting package or packages.

By default, the value of this variable is set to [TUNE\\_PKGARCH](#) when building for the target, [BUILD\\_ARCH](#) when building for the build host, and `"${SDK_ARCH}-${SDKPKGSUFFIX}"` when building for the SDK.

#### **Nota**

See [SDK\\_ARCH](#) for more information.

However, if your recipe's output packages are built specific to the target machine rather than generally for the architecture of the machine, you should set [PACKAGE\\_ARCH](#) to the value of [MACHINE\\_ARCH](#) in the recipe as follows:

```
PACKAGE_ARCH = "${MACHINE_ARCH}"
```

## **PACKAGE\_ARCHS**

Specifies a list of architectures compatible with the target machine. This variable is set automatically and should

not normally be hand-edited. Entries are separated using spaces and listed in order of priority. The default value for `PACKAGE_ARCHS` is "all any noarch \${PACKAGE\_EXTRA\_ARCHS} \${MACHINE\_ARCH}".

### `PACKAGE_BEFORE_PN`

Enables easily adding packages to `PACKAGES` before `${PN}` so that those added packages can pick up files that would normally be included in the default package.

### `PACKAGE_CLASSES`

This variable specifies the package manager the OpenEmbedded build system uses when packaging data.

You can provide one or more of the following arguments for the variable:

```
PACKAGE_CLASSES ?= "package_rpm package_deb package_ipk"
```

The build system uses only the first argument in the list as the package manager when creating your image or SDK. However, packages will be created using any additional packaging classes you specify. For example, if you use the following in your distro *configuration file*:

```
PACKAGE_CLASSES ?= "package_ipk"
```

The OpenEmbedded build system uses the IPK package manager to create your image or SDK.

For information on packaging and build performance effects as a result of the package manager in use, see the "*package*" section.

### `PACKAGE_DEBUG_SPLIT_STYLE`

Determines how to split up and package debug and source information when creating debugging packages to be used with the GNU Project Debugger (GDB). In general, based on the value of this variable, you can combine the source and debug info in a single package, you can break out the source into a separate package that can be installed independently, or you can choose to not have the source packaged at all.

The possible values of `PACKAGE_DEBUG_SPLIT_STYLE` variable:

- `".debug"`: All debugging and source info is placed in a single `*-dbg` package; debug symbol files are placed next to the binary in a `.debug` directory so that, if a binary is installed into `/bin`, the corresponding debug symbol file is installed in `/bin/.debug`. Source files are installed in the same `*-dbg` package under `/usr/src/debug`.
- `"debug-file-directory"`: As above, all debugging and source info is placed in a single `*-dbg` package; debug symbol files are placed entirely under the directory `/usr/lib/debug` and separated by the path from where the binary is installed, so that if a binary is installed in `/bin`, the corresponding debug symbols are installed in `/usr/lib/debug/bin`, and so on. As above, source is installed in the same package under `/usr/src/debug`.
- `"debug-with-srcpkg"`: Debugging info is placed in the standard `*-dbg` package as with the `.debug` value, while source is placed in a separate `*-src` package, which can be installed independently. This is the default setting for this variable, as defined in *OE-Core's* `bitbake.conf` file.
- `"debug-without-src"`: The same behavior as with the `.debug` setting, but no source is packaged at all.

**i Nota**

Much of the above package splitting can be overridden via use of the `INHIBIT_PACKAGE_DEBUG_SPLIT` variable.

You can find out more about debugging using GDB by reading the "*Debugging With the GNU Project Debugger (GDB) Remotely*" section in the Yocto Project Development Tasks Manual.

**PACKAGE\_EXCLUDE**

Lists packages that should not be installed into an image. For example:

```
PACKAGE_EXCLUDE = "package_name package_name package_name ..."
```

You can set this variable globally in a *configuration file* or you can specify it in an image recipe directly:

```
PACKAGE_EXCLUDE = "package_name"
```

If you choose to not install a package using this variable and some other package is dependent on it (i.e. listed in a recipe's `RDEPENDS` variable), the OpenEmbedded build system generates a fatal installation error. Because the build system halts the process with a fatal error, you can use the variable with an iterative development process to remove specific components from a system.

This variable is supported for all packaging backends.

See the `NO_RECOMMENDATIONS` and the `BAD_RECOMMENDATIONS` variables for related information.

**PACKAGE\_EXCLUDE\_COMPLEMENTARY**

Prevents specific packages from being installed when you are installing complementary packages.

You might find that you want to prevent installing certain packages when you are installing complementary packages. For example, if you are using `IMAGE_FEATURES` to install `dev-pkgs`, you might not want to install all packages from a particular multilib. If you find yourself in this situation, you can use the `PACKAGE_EXCLUDE_COMPLEMENTARY` variable to specify regular expressions to match the packages you want to exclude.

**PACKAGE\_EXTRA\_ARCHS**

Specifies the list of architectures compatible with the device CPU. This variable is useful when you build for several different devices that use miscellaneous processors such as XScale and ARM926-EJS.

**PACKAGE\_FEED\_ARCHS**

Optionally specifies the package architectures used as part of the package feed URIs during the build. When used, the `PACKAGE_FEED_ARCHS` variable is appended to the final package feed URI, which is constructed using the `PACKAGE_FEED_URIS` and `PACKAGE_FEED_BASE_PATHS` variables.

**i Nota**

You can use the `PACKAGE_FEED_ARCHS` variable to allow specific package architectures. If you do not need to allow specific architectures, which is a common case, you can omit this variable. Omitting the

variable results in all available architectures for the current machine being included into remote package feeds.

Consider the following example where the *PACKAGE\_FEED\_URI*, *PACKAGE\_FEED\_BASE\_PATHS*, and *PACKAGE\_FEED\_ARCHS* variables are defined in your *build/conf/local.conf* file:

```
PACKAGE_FEED_URI = "https://example.com/packagerepos/release \
                   https://example.com/packagerepos/updates"
PACKAGE_FEED_BASE_PATHS = "rpm rpm-dev"
PACKAGE_FEED_ARCHS = "all core2-64"
```

Given these settings, the resulting package feeds are as follows:

```
https://example.com/packagerepos/release/rpm/all
https://example.com/packagerepos/release/rpm/core2-64
https://example.com/packagerepos/release/rpm-dev/all
https://example.com/packagerepos/release/rpm-dev/core2-64
https://example.com/packagerepos/updates/rpm/all
https://example.com/packagerepos/updates/rpm/core2-64
https://example.com/packagerepos/updates/rpm-dev/all
https://example.com/packagerepos/updates/rpm-dev/core2-64
```

### *PACKAGE\_FEED\_BASE\_PATHS*

Specifies the base path used when constructing package feed URIs. The *PACKAGE\_FEED\_BASE\_PATHS* variable makes up the middle portion of a package feed URI used by the OpenEmbedded build system. The base path lies between the *PACKAGE\_FEED\_URI* and *PACKAGE\_FEED\_ARCHS* variables.

Consider the following example where the *PACKAGE\_FEED\_URI*, *PACKAGE\_FEED\_BASE\_PATHS*, and *PACKAGE\_FEED\_ARCHS* variables are defined in your *build/conf/local.conf* file:

```
PACKAGE_FEED_URI = "https://example.com/packagerepos/release \
                   https://example.com/packagerepos/updates"
PACKAGE_FEED_BASE_PATHS = "rpm rpm-dev"
PACKAGE_FEED_ARCHS = "all core2-64"
```

Given these settings, the resulting package feeds are as follows:

```
https://example.com/packagerepos/release/rpm/all
https://example.com/packagerepos/release/rpm/core2-64
https://example.com/packagerepos/release/rpm-dev/all
https://example.com/packagerepos/release/rpm-dev/core2-64
https://example.com/packagerepos/updates/rpm/all
https://example.com/packagerepos/updates/rpm/core2-64
https://example.com/packagerepos/updates/rpm-dev/all
https://example.com/packagerepos/updates/rpm-dev/core2-64
```



### ***PACKAGE\_FEED\_URI***

Specifies the front portion of the package feed URI used by the OpenEmbedded build system. Each final package feed URI is comprised of *PACKAGE\_FEED\_URI*, *PACKAGE\_FEED\_BASE\_PATHS*, and *PACKAGE\_FEED\_ARCHS* variables.

Consider the following example where the *PACKAGE\_FEED\_URI*, *PACKAGE\_FEED\_BASE\_PATHS*, and *PACKAGE\_FEED\_ARCHS* variables are defined in your *build/conf/local.conf* file:

```
PACKAGE_FEED_URI = "https://example.com/packagerepos/release \
                    https://example.com/packagerepos/updates"
PACKAGE_FEED_BASE_PATHS = "rpm rpm-dev"
PACKAGE_FEED_ARCHS = "all core2-64"
```

Given these settings, the resulting package feeds are as follows:

```
https://example.com/packagerepos/release/rpm/all
https://example.com/packagerepos/release/rpm/core2-64
https://example.com/packagerepos/release/rpm-dev/all
https://example.com/packagerepos/release/rpm-dev/core2-64
https://example.com/packagerepos/updates/rpm/all
https://example.com/packagerepos/updates/rpm/core2-64
https://example.com/packagerepos/updates/rpm-dev/all
https://example.com/packagerepos/updates/rpm-dev/core2-64
```

### ***PACKAGE\_INSTALL***

The final list of packages passed to the package manager for installation into the image.

Because the package manager controls actual installation of all packages, the list of packages passed using *PACKAGE\_INSTALL* is not the final list of packages that are actually installed. This variable is internal to the image construction code. Consequently, in general, you should use the *IMAGE\_INSTALL* variable to specify packages for installation. The exception to this is when working with the *core-image-minimal-initramfs* image. When working with an initial RAM filesystem (*Initramfs*) image, use the *PACKAGE\_INSTALL* variable. For information on creating an *Initramfs*, see the "*Building an Initial RAM Filesystem (Initramfs) Image*" section in the Yocto Project Development Tasks Manual.

### ***PACKAGE\_INSTALL\_ATTEMPTONLY***

Specifies a list of packages the OpenEmbedded build system attempts to install when creating an image. If a listed package fails to install, the build system does not generate an error. This variable is generally not user-defined.

### ***PACKAGE\_NO\_LOCALE***

The *PACKAGE\_NO\_LOCALE* variable can be set to "1" to prevent the *OpenEmbedded Build System* from splitting the locales found in the *PKGDIR* directory into split packages.

For example, the *quilt* recipe automatically produces split packages after the *do\_package* task is run. Taking a look inside the *WORKDIR* directory of *quilt*:

```
$ ls -1 packages-split/  
guards  
guards-doc  
quilt  
quilt-dbg  
quilt-dev  
quilt-doc  
quilt-locale-de  
quilt-locale-fr  
quilt-locale-ja  
quilt-locale-ru  
quilt-ptest  
quilt-src  
quilt-staticdev
```

We can see the `quilt-locale-*` packages were automatically generated. Setting `PACKAGE_NO_LOCALE` to "1" would produce the following packages:

```
$ ls -1 packages-split/  
guards  
guards-doc  
quilt  
quilt-dbg  
quilt-dev  
quilt-doc  
quilt-locale  
quilt-ptest  
quilt-src  
quilt-staticdev
```

The `quilt-locale` package contains the merged content of the previous `quilt-locale-*` packages.

#### ***PACKAGE\_PREPROCESS\_FUNCS***

Specifies a list of functions run to pre-process the *PKGD* directory prior to splitting the files out to individual packages.

#### ***PACKAGE\_WRITE\_DEPS***

Specifies a list of dependencies for post-installation and pre-installation scripts on native/cross tools. If your post-installation or pre-installation script can execute at root filesystem creation time rather than on the target but depends on a native tool in order to execute, you need to list the tools in *PACKAGE\_WRITE\_DEPS*.

For information on running post-installation scripts, see the "*Post-Installation Scripts*" section in the Yocto Project Development Tasks Manual.

#### ***PACKAGECONFIG***

This variable provides a means of enabling or disabling features of a recipe on a per-recipe basis. *PACKA-*

*GECONFIG* blocks are defined in recipes when you specify features and then arguments that define feature behaviors. Here is the basic block structure (broken over multiple lines for readability):

```
PACKAGECONFIG ??= "f1 f2 f3 ..."
PACKAGECONFIG[f1] = "\
    --with-f1, \
    --without-f1, \
    build-deps-for-f1, \
    runtime-deps-for-f1, \
    runtime-recommends-for-f1, \
    packageconfig-conflicts-for-f1"
PACKAGECONFIG[f2] = "\
    ... and so on and so on ...
```

The *PACKAGECONFIG* variable itself specifies a space-separated list of the features to enable. Following the features, you can determine the behavior of each feature by providing up to six order-dependent arguments, which are separated by commas. You can omit any argument you like but must retain the separating commas. The order is important and specifies the following:

1. Extra arguments that should be added to *PACKAGECONFIG\_CONFARGS* if the feature is enabled.
2. Extra arguments that should be added to *PACKAGECONFIG\_CONFARGS* if the feature is disabled.
3. Additional build dependencies (*DEPENDS*) that should be added if the feature is enabled.
4. Additional runtime dependencies (*RDEPENDS*) that should be added if the feature is enabled.
5. Additional runtime recommendations (*RRECOMMENDS*) that should be added if the feature is enabled.
6. Any conflicting (that is, mutually exclusive) *PACKAGECONFIG* settings for this feature.

Consider the following *PACKAGECONFIG* block taken from the `librsvg` recipe. In this example the feature is `gtk`, which has three arguments that determine the feature's behavior:

```
PACKAGECONFIG[gtk] = "--with-gtk3,--without-gtk3,gtk+3"
```

The `--with-gtk3` and `gtk+3` arguments apply only if the feature is enabled. In this case, `--with-gtk3` is added to the configure script argument list and `gtk+3` is added to *DEPENDS*. On the other hand, if the feature is disabled say through a `.bbappend` file in another layer, then the second argument `--without-gtk3` is added to the configure script instead.

The basic *PACKAGECONFIG* structure previously described holds true regardless of whether you are creating a block or changing a block. When creating a block, use the structure inside your recipe.

If you want to change an existing *PACKAGECONFIG* block, you can do so one of two ways:

- *Append file*: Create an append file named `recipename.bbappend` in your layer and override the value of *PACKAGECONFIG*. You can either completely override the variable:

```
PACKAGECONFIG = "f4 f5"
```

Or, you can just append the variable:

```
PACKAGECONFIG:append = " f4"
```

- *Configuration file*: This method is identical to changing the block through an append file except you edit your *build/conf/local.conf* or distro *configuration file*. As with append files previously described, you can either completely override the variable:

```
PACKAGECONFIG:pn-recipe = "f4 f5"
```

Or, you can just amend the variable:

```
PACKAGECONFIG:append:pn-recipe = " f4"
```

Consider the following example of a *cmake* recipe with a systemd service in which *PACKAGECONFIG* is used to transform the systemd service into a feature that can be easily enabled or disabled via *PACKAGECONFIG*:

```
example.c
example.service
CMakeLists.txt
```

The *CMakeLists.txt* file contains:

```
if(WITH_SYSTEMD)
    install(FILES ${PROJECT_SOURCE_DIR}/example.service DESTINATION /etc/
↳systemd/systemd)
endif(WITH_SYSTEMD)
```

In order to enable the installation of *example.service* we need to ensure that *-DWITH\_SYSTEMD=ON* is passed to the *cmake* command execution. Recipes that have *CMakeLists.txt* generally inherit the *cmake* class, that runs *cmake* with *EXTRA\_OECMAKE*, which *PACKAGECONFIG\_CONFARGS* will be appended to. Now, knowing that *PACKAGECONFIG\_CONFARGS* is automatically filled with either the first or second element of *PACKAGECONFIG* flag value, the recipe would be like:

```
inherit cmake
PACKAGECONFIG = "systemd"
PACKAGECONFIG[systemd] = "-DWITH_SYSTEMD=ON,-DWITH_SYSTEMD=OFF"
```

A side note to this recipe is to check if *systemd* is in fact the used *INIT\_MANAGER* or not:

```
PACKAGECONFIG = "${@'systemd' if d.getVar('INIT_MANAGER') == 'systemd' else ''}
↳"
```

## PACKAGECONFIG\_CONFARGS

A space-separated list of configuration options generated from the *PACKAGECONFIG* setting.

Classes such as *autotools\** and *cmake* use *PACKAGECONFIG\_CONFARGS* to pass *PACKAGECONFIG* options to *configure* and *cmake*, respectively. If you are using *PACKAGECONFIG* but not a class that handles the *do\_configure* task, then you need to use *PACKAGECONFIG\_CONFARGS* appropriately.

## PACKAGEFUNCS

The *PACKAGEFUNCS* variable holds a list of functions which are executed to process metadata based on split packages found in the *PKGDEST* directory. These functions are executed in the *package* class in the order found in the list.

## PACKAGEGROUP\_DISABLE\_COMPLEMENTARY

For recipes inheriting the *packagegroup* class, setting *PACKAGEGROUP\_DISABLE\_COMPLEMENTARY* to "1" specifies that the normal complementary packages (i.e. *-dev*, *-dbg*, and so forth) should not be automatically created by the *packagegroup* recipe, which is the default behavior.

## PACKAGES

The list of packages the recipe creates. The default value is the following:

```
${PN}-src ${PN}-dbg ${PN}-staticdev ${PN}-dev ${PN}-doc ${PN}-locale ${PACKAGE_
↪BEFORE_PN} ${PN}
```

During packaging, the *do\_package* task goes through *PACKAGES* and uses the *FILES* variable corresponding to each package to assign files to the package. If a file matches the *FILES* variable for more than one package in *PACKAGES*, it will be assigned to the earliest (leftmost) package.

Packages in the variable's list that are empty (i.e. where none of the patterns in *FILES:pkg* match any files installed by the *do\_install* task) are not generated, unless generation is forced through the *ALLOW\_EMPTY* variable.

## PACKAGES\_DYNAMIC

A promise that your recipe satisfies runtime dependencies for optional modules that are found in other recipes. *PACKAGES\_DYNAMIC* does not actually satisfy the dependencies, it only states that they should be satisfied. For example, if a hard, runtime dependency (*RDEPENDS*) of another package is satisfied at build time through the *PACKAGES\_DYNAMIC* variable, but a package with the module name is never actually produced, then the other package will be broken. Thus, if you attempt to include that package in an image, you will get a dependency failure from the packaging system during the *do\_rootfs* task.

Typically, if there is a chance that such a situation can occur and the package that is not created is valid without the dependency being satisfied, then you should use *RRECOMMENDS* (a soft runtime dependency) instead of *RDEPENDS*.

For an example of how to use the *PACKAGES\_DYNAMIC* variable when you are splitting packages, see the "*Handling Optional Module Packaging*" section in the Yocto Project Development Tasks Manual.

## PACKAGESPLITFUNCS

Specifies a list of functions run to perform additional splitting of files into individual packages. Recipes can either prepend to this variable or prepend to the *populate\_packages* function in order to perform additional package splitting. In either case, the function should set *PACKAGES*, *FILES*, *RDEPENDS* and other packaging variables appropriately in order to perform the desired splitting.

## PARALLEL\_MAKE

Extra options passed to the build tool command (*make*, *ninja* or more specific build engines, like the Go language one) during the *do\_compile* task, to specify parallel compilation on the local build host. This variable is usually in the form "*-j x*", where *x* represents the maximum number of parallel threads such engines can run.

**i Nota**

For software compiled by `make`, in order for `PARALLEL_MAKE` to be effective, `make` must be called with `#{EXTRA_OEMAKE}`. An easy way to ensure this is to use the `oe_runmake` function.

By default, the OpenEmbedded build system automatically sets this variable to be equal to the number of cores the build system uses.

**i Nota**

If the software being built experiences dependency issues during the `do_compile` task that result in race conditions, you can clear the `PARALLEL_MAKE` variable within the recipe as a workaround. For information on addressing race conditions, see the "*Debugging Parallel Make Races*" section in the Yocto Project Development Tasks Manual.

For single socket systems (i.e. one CPU), you should not have to override this variable to gain optimal parallelism during builds. However, if you have very large systems that employ multiple physical CPUs, you might want to make sure the `PARALLEL_MAKE` variable is not set higher than `"-j 20"`.

For more information on speeding up builds, see the "*Speeding Up a Build*" section in the Yocto Project Development Tasks Manual.

For more information on how to limit the resources used during builds, see the *Limiting the Host Resources Usage* section of the Yocto Project Development Tasks Manual.

**PARALLEL\_MAKEINST**

Extra options passed to the build tool install command (`make install`, `ninja install` or more specific ones) during the `do_install` task in order to specify parallel installation. This variable defaults to the value of `PARALLEL_MAKE`.

**i Nota**

For software compiled by `make`, in order for `PARALLEL_MAKEINST` to be effective, `make` must be called with `#{EXTRA_OEMAKE}`. An easy way to ensure this is to use the `oe_runmake` function.

If the software being built experiences dependency issues during the `do_install` task that result in race conditions, you can clear the `PARALLEL_MAKEINST` variable within the recipe as a workaround. For information on addressing race conditions, see the "*Debugging Parallel Make Races*" section in the Yocto Project Development Tasks Manual.

**PATCHRESOLVE**

Determines the action to take when a patch fails. You can set this variable to one of two values: `"noop"` and `"user"`.

The default value of `"noop"` causes the build to simply fail when the OpenEmbedded build system cannot successfully apply a patch. Setting the value to `"user"` causes the build system to launch a shell and places you in the right location so that you can manually resolve the conflicts.

Set this variable in your *build/conf/local.conf* file.

### PATCHTOOL

Specifies the utility used to apply patches for a recipe during the *do\_patch* task. You can specify one of three utilities: "patch", "quilt", or "git". The default utility used is "quilt" except for the quilt-native recipe itself. Because the quilt tool is not available at the time quilt-native is being patched, it uses "patch".

If you wish to use an alternative patching tool, set the variable in the recipe using one of the following:

```
PATCHTOOL = "patch"
PATCHTOOL = "quilt"
PATCHTOOL = "git"
```

### PE

The epoch of the recipe. By default, this variable is unset. The variable is used to make upgrades possible when the versioning scheme changes in some backwards incompatible way.

*PE* is the default value of the *PKG* variable.

### PEP517\_WHEEL\_PATH

When used by recipes that inherit the *python\_pep517* class, denotes the path to *dist/* (short for distribution) where the binary archive *wheel* is built.

### PERSISTENT\_DIR

See *PERSISTENT\_DIR* in the BitBake manual.

### PF

Specifies the recipe or package name and includes all version and revision numbers (i.e. *glibc-2.13-r20+svnr15508/* and *bash-4.2-r1/*). This variable is comprised of the following: *\${PN}-\${EXTENDPE}\${PV}-\${PR}*

### PIXBUF\_PACKAGES

When inheriting the *pixbufcache* class, this variable identifies packages that contain the pixbuf loaders used with *gdk-pixbuf*. By default, the *pixbufcache* class assumes that the loaders are in the recipe's main package (i.e. *\${PN}*). Use this variable if the loaders you need are in a package other than that main package.

### PKG

The name of the resulting package created by the OpenEmbedded build system.

#### Nota

When using the *PKG* variable, you must use a package name override.

For example, when the *debian* class renames the output package, it does so by setting *PKG:packagename*.

### PKG\_CONFIG\_PATH

The path to *pkg-config* files for the current build context. *pkg-config* reads this variable from the environment.

### **PKGDIR**

Points to the destination directory for files to be packaged before they are split into individual packages. This directory defaults to the following:

```
${WORKDIR}/package
```

Do not change this default.

### **PKGDATA\_DIR**

Points to a shared, global-state directory that holds data generated during the packaging process. During the packaging process, the *do\_packagedata* task packages data for each recipe and installs it into this shared area. This directory defaults to the following, which you should not change:

```
${TMPDIR}/pkgdata/${MACHINE}
```

For examples of how this data is used, see the "*Dipendenze di Runtime Aggiunte Automaticamente*" section in the Yocto Project Overview and Concepts Manual and the "*Viewing Package Information with oe-pkgdata-util*" section in the Yocto Project Development Tasks Manual.

### **PKGDEST**

Points to the parent directory for files to be packaged after they have been split into individual packages. This directory defaults to the following:

```
${WORKDIR}/packages-split
```

Under this directory, the build system creates directories for each package specified in *PACKAGES*. Do not change this default.

### **PKGDESTWORK**

Points to a temporary work area where the *do\_package* task saves package metadata. The *PKGDESTWORK* location defaults to the following:

```
${WORKDIR}/pkgdata
```

Do not change this default.

The *do\_packagedata* task copies the package metadata from *PKGDESTWORK* to *PKGDATA\_DIR* to make it available globally.

### **PKGGE**

The epoch of the package(s) built by the recipe. By default, *PKGGE* is set to *PE*.

### **PKGR**

The revision of the package(s) built by the recipe. By default, *PKGR* is set to *PR*.

### **PKGVS**

The version of the package(s) built by the recipe. By default, *PKGVS* is set to *PV*.

If *PV* contains the + sign, source control information will be included in *PKGVS* later in the packaging phase. For more information, see the *Using an External SCM* section of the Yocto Project Development Tasks Manual.



**⚠ Avvertimento**

Since source control information is included in a late stage by the *package* class, it cannot be seen from the BitBake environment with `bitbake -e` or `bitbake-getvar`. Instead, after the package is built, the version information can be retrieved with `oe-pkgdata-util package-info <package name>`. See the *Viewing Package Information with oe-pkgdata-util* section of the Yocto Project Development Tasks Manual for more information on `oe-pkgdata-util`.

***PN***

This variable can have two separate functions depending on the context: a recipe name or a resulting package name.

*PN* refers to a recipe name in the context of a file used by the OpenEmbedded build system as input to create a package. The name is normally extracted from the recipe file name. For example, if the recipe is named `expat_2.0.1.bb`, then the default value of *PN* will be "expat".

The variable refers to a package name in the context of a file created or produced by the OpenEmbedded build system.

If applicable, the *PN* variable also contains any special suffix or prefix. For example, using `bash` to build packages for the native machine, *PN* is `bash-native`. Using `bash` to build packages for the target and for Multilib, *PN* would be `bash` and `lib64-bash`, respectively.

***POPULATE\_SDK\_POST\_HOST\_COMMAND***

Specifies a list of functions to call once the OpenEmbedded build system has created the host part of the SDK. You can specify functions separated by spaces:

```
POPULATE_SDK_POST_HOST_COMMAND += "function"
```

If you need to pass the SDK path to a command within a function, you can use `${SDK_DIR}`, which points to the parent directory used by the OpenEmbedded build system when creating SDK output. See the *SDK\_DIR* variable for more information.

***POPULATE\_SDK\_POST\_TARGET\_COMMAND***

Specifies a list of functions to call once the OpenEmbedded build system has created the target part of the SDK. You can specify functions separated by spaces:

```
POPULATE_SDK_POST_TARGET_COMMAND += "function"
```

If you need to pass the SDK path to a command within a function, you can use `${SDK_DIR}`, which points to the parent directory used by the OpenEmbedded build system when creating SDK output. See the *SDK\_DIR* variable for more information.

***PR***

The revision of the recipe. The default value for this variable is "r0". Subsequent revisions of the recipe conventionally have the values "r1", "r2", and so forth. When *PV* increases, *PR* is conventionally reset to "r0".

**i Nota**

The OpenEmbedded build system does not need the aid of *PR* to know when to rebuild a recipe. The build system uses the task *input checksums* along with the *stamp* and *Cache di Shared State* mechanisms.

The *PR* variable primarily becomes significant when a package manager dynamically installs packages on an already built image. In this case, *PR*, which is the default value of *PKGR*, helps the package manager distinguish which package is the most recent one in cases where many packages have the same *PV* (i.e. *PKGVS*). A component having many packages with the same *PV* usually means that the packages all install the same upstream version, but with later (*PR*) version packages including packaging fixes.

**i Nota**

*PR* does not need to be increased for changes that do not change the package contents or metadata.

Because manually managing *PR* can be cumbersome and error-prone, an automated solution exists. See the "*Working With a PR Service*" section in the Yocto Project Development Tasks Manual for more information.

**PREFERRED\_PROVIDER**

If multiple recipes provide the same item, this variable determines which recipe is preferred and thus provides the item (i.e. the preferred provider). You should always suffix this variable with the name of the provided item. And, you should define the variable using the preferred recipe's name (*PN*). Here is a common example:

```
PREFERRED_PROVIDER_virtual/kernel ?= "linux-yocto"
```

In the previous example, multiple recipes are providing "virtual/kernel". The *PREFERRED\_PROVIDER* variable is set with the name (*PN*) of the recipe you prefer to provide "virtual/kernel".

Here are more examples:

```
PREFERRED_PROVIDER_virtual/xserver = "xserver-xf86"
PREFERRED_PROVIDER_virtual/libgl ?= "mesa"
```

For more information, see the "*Using Virtual Providers*" section in the Yocto Project Development Tasks Manual.

**i Nota**

If you use a `virtual/*` item with *PREFERRED\_PROVIDER*, then any recipe that *PROVIDES* that item but is not selected (defined) by *PREFERRED\_PROVIDER* is prevented from building, which is usually desirable since this mechanism is designed to select between mutually exclusive alternative providers.

**PREFERRED\_PROVIDERS**

See *PREFERRED\_PROVIDERS* in the BitBake manual.

**PREFERRED\_RPROVIDER**

The *PREFERRED\_RPROVIDER* variable works like the *PREFERRED\_PROVIDER* variable, but it denotes pac-

kages that provide a *runtime* component. Runtime providers are declared in recipes that set the *RPROVIDES* variable for a specific package.

Per esempio:

```
PREFERRED_RPROVIDER_virtual-x-terminal-emulator = "rxvt-unicode"
```

This statement sets the runtime provider for the X terminal emulator to `rxvt-unicode`. The `rxvt-unicode` package is a runtime provider of this component because the `rxvt-unicode` recipe set the following *RPROVIDES* definition for the `rxvt-unicode` (`{PN}`) package:

```
RPROVIDES:${PN} = "virtual-x-terminal-emulator"
```

For more information on virtual providers, see the "*Using Virtual Providers*" section in the Yocto Project Development Tasks Manual.

### ***PREFERRED\_TOOLCHAIN***

The *PREFERRED\_TOOLCHAIN* variable selects the toolchain to use for compiling recipes. This variable is not meant to be overridden globally. Instead, the values of *PREFERRED\_TOOLCHAIN\_TARGET*, *PREFERRED\_TOOLCHAIN\_NATIVE* and *PREFERRED\_TOOLCHAIN\_SDK* should be overridden.

### ***PREFERRED\_TOOLCHAIN\_NATIVE***

This variable controls the toolchain used for compiling *native* recipes.

This variable should be set globally from a *configuration file*.

See *PREFERRED\_TOOLCHAIN\_TARGET* for more details on the possible values for this variable.

A recipe that does not support the toolchain specified by *PREFERRED\_TOOLCHAIN\_NATIVE* can override it locally with *TOOLCHAIN\_NATIVE*.

### ***PREFERRED\_TOOLCHAIN\_SDK***

This variable controls the toolchain used for compiling *nativesdk* recipes.

This variable should be set globally from a *configuration file*.

See *PREFERRED\_TOOLCHAIN\_TARGET* for more details on the possible values for this variable.

### ***PREFERRED\_TOOLCHAIN\_TARGET***

This variable controls the toolchain used for compiling recipes in the architecture of the target *MACHINE*.

There are two possible values for this variable at the moment:

- *gcc* (default): the GCC/Binutils toolchain.
- *clang*: the Clang/LLVM toolchain.

*PREFERRED\_TOOLCHAIN\_TARGET* will make the *base* class inherit one of the toolchain classes defined in *meta/classes/toolchain*. As a consequence, this variable should be set globally from a *configuration file*.

These classes define commands used for cross-compiling such as *CC*, *CXX*, *LD* and so on.

A recipe that does not support the toolchain specified by *PREFERRED\_TOOLCHAIN\_TARGET* can override it locally with *TOOLCHAIN*.

### *PREFERRED\_VERSION*

If there are multiple versions of a recipe available, this variable determines which version should be given preference. You must always suffix the variable with the *PN* you want to select (*python* in the first example below), and you should specify the *PV* accordingly (3.4.0 in the example).

The *PREFERRED\_VERSION* variable supports limited wildcard use through the "%" character. You can use the character to match any number of characters, which can be useful when specifying versions that contain long revision numbers that potentially change. Here are two examples:

```
PREFERRED_VERSION_python = "3.4.0"
PREFERRED_VERSION_linux-yocto = "5.0%"
```

#### **i** Nota

The use of the "%" character is limited in that it only works at the end of the string. You cannot use the wildcard character in any other location of the string.

The specified version is matched against *PV*, which does not necessarily match the version part of the recipe's filename.

If you want to select a recipe named `foo_git.bb` which has *PV* set to `1.2.3+git`, you can do so by setting `PREFERRED_VERSION_foo` to `1.2.3%` (i.e. simply setting `PREFERRED_VERSION_foo` to `git` will not work as the name of the recipe isn't used, but rather its *PV* definition).

Sometimes the *PREFERRED\_VERSION* variable can be set by configuration files in a way that is hard to change. You can use *OVERRIDES* to set a machine-specific override. Here is an example:

```
PREFERRED_VERSION_linux-yocto:qemux86 = "5.0%"
```

Although not recommended, worst case, you can also use the "forcevariable" override, which is the strongest override possible. Here is an example:

```
PREFERRED_VERSION_linux-yocto:forcevariable = "5.0%"
```

#### **i** Nota

The `:forcevariable` override is not handled specially. This override only works because the default value of *OVERRIDES* includes "forcevariable".

If a recipe with the specified version is not available, a warning message will be shown. See *REQUIRED\_VERSION* if you want this to be an error instead.

### *PREMIRRORS*

Specifies additional paths from which the OpenEmbedded build system gets source code. When the build system searches for source code, it first tries the local download directory. If that location fails, the build system tries locations defined by *PREMIRRORS*, the upstream source, and then locations specified by *MIRRORS* in that order.

The default value for *PREMIRRORS* is defined in the `meta/classes-global/mirrors.bbclass` file in the core metadata layer.

Typically, you could add a specific server for the build system to attempt before any others by adding something like the following to the `build/conf/site.conf` configuration file in the *Build Directory*:

```
PREMIRRORS:prepend = "\
    git://.*.* https://downloads.yoctoproject.org/mirror/sources/ \
    ftp://.*.* https://downloads.yoctoproject.org/mirror/sources/ \
    http://.*.* https://downloads.yoctoproject.org/mirror/sources/ \
    https://.*.* https://downloads.yoctoproject.org/mirror/sources/ \
"
```

These changes cause the build system to intercept Git, FTP, HTTP, and HTTPS requests and direct them to the `http://` sources mirror. You can use `file://` URLs to point to local directories or network shares as well.

See the definition of this variable in the BitBake Manual for more details: [PREMIRRORS](#).

### *PRIORITY*

Indicates the importance of a package.

*PRIORITY* is considered to be part of the distribution policy because the importance of any given recipe depends on the purpose for which the distribution is being produced. Thus, *PRIORITY* is not normally set within recipes.

You can set *PRIORITY* to "required", "standard", "extra", and "optional", which is the default.

### *PRIVATE\_LIBS*

Specifies libraries installed within a recipe that should be ignored by the OpenEmbedded build system's shared library resolver. This variable is typically used when software being built by a recipe has its own private versions of a library normally provided by another recipe. In this case, you would not want the package containing the private libraries to be set as a dependency on other unrelated packages that should instead depend on the package providing the standard version of the library.

Libraries specified in this variable should be specified by their file name. For example, from the Firefox recipe in `meta-browser`:

```
PRIVATE_LIBS = "libmozjs.so \
    libxpcom.so \
    libnspr4.so \
    libxul.so \
    libmozalloc.so \
    libplc4.so \
    libplds4.so"
```

For more information, see the "*Dipendenze di Runtime Aggiunte Automaticamente*" section in the Yocto Project Overview and Concepts Manual.

### *PROVIDES*

A list of aliases by which a particular recipe can be known. By default, a recipe's own *PN* is implicitly already

in its *PROVIDES* list and therefore does not need to mention that it provides itself. If a recipe uses *PROVIDES*, the additional aliases are synonyms for the recipe and can be useful for satisfying dependencies of other recipes during the build as specified by *DEPENDS*.

Consider the following example *PROVIDES* statement from the recipe file `eudev_3.2.9.bb`:

```
PROVIDES += "udev"
```

The *PROVIDES* statement results in the "eudev" recipe also being available as simply "udev".

#### Nota

A recipe's own recipe name (*PN*) is always implicitly prepended to *PROVIDES*, so while using "+" in the above example may not be strictly necessary it is recommended to avoid confusion.

In addition to providing recipes under alternate names, the *PROVIDES* mechanism is also used to implement virtual targets. A virtual target is a name that corresponds to some particular functionality (e.g. a Linux kernel). Recipes that provide the functionality in question list the virtual target in *PROVIDES*. Recipes that depend on the functionality in question can include the virtual target in *DEPENDS* to leave the choice of provider open.

Conventionally, virtual targets have names on the form "virtual/function" (e.g. "virtual/kernel"). The slash is simply part of the name and has no syntactical significance.

The *PREFERRED\_PROVIDER* variable is used to select which particular recipe provides a virtual target.

#### Nota

A corresponding mechanism for virtual runtime dependencies (packages) exists. However, the mechanism does not depend on any special functionality beyond ordinary variable assignments. For example, *VIRTUAL-RUNTIME\_dev\_manager* refers to the package of the component that manages the `/dev` directory.

Setting the "preferred provider" for runtime dependencies is as simple as using the following assignment in a configuration file:

```
VIRTUAL-RUNTIME_dev_manager = "udev"
```

## *PRSERV\_HOST*

The network based *PR* service host and port.

The `meta/conf/templates/default/local.conf.sample.extended` configuration file in *OpenEmbedded-Core (OE-Core)* shows how the *PRSERV\_HOST* variable is set:

```
PRSERV_HOST = "localhost:0"
```

You must set the variable if you want to automatically start a local *PR service*. You can set *PRSERV\_HOST* to other values to use a remote PR service.

### ***PRSERV\_UPSTREAM***

This variable can be used to specify an upstream PR server for the local PR server to connect to, in the form of `host:port`.

This makes it possible to implement local fixes to an upstream package.

### ***PSEUDO\_IGNORE\_PATHS***

A comma-separated (without spaces) list of path prefixes that should be ignored by pseudo when monitoring and recording file operations, in order to avoid problems with files being written to outside of the pseudo context and reduce pseudo's overhead. A path is ignored if it matches any prefix in the list and can include partial directory (or file) names. In case a path prefix is present in both *PSEUDO\_IGNORE\_PATHS* and in *PSEUDO\_INCLUDE\_PATHS*, *PSEUDO\_INCLUDE\_PATHS* takes precedence.

### ***PSEUDO\_INCLUDE\_PATHS***

A comma-separated (without spaces) list of path prefixes that should be included by pseudo when monitoring and recording file operations, in order to avoid problems with files being written to outside of the pseudo context and reduce *pseudo*'s overhead. A path is included if it matches any prefix in the list and can include partial directory (or file) names. In case a path prefix is present in both *PSEUDO\_IGNORE\_PATHS* and in *PSEUDO\_INCLUDE\_PATHS*, *PSEUDO\_INCLUDE\_PATHS* takes precedence.

### ***PTEST\_ENABLED***

Specifies whether or not *Package Test* (ptest) functionality is enabled when building a recipe. You should not set this variable directly. Enabling and disabling building Package Tests at build time should be done by adding "ptest" to (or removing it from) *DISTRO\_FEATURES*.

### ***PTEST\_PYTEST\_DIR***

Within the *ptest-python-pytest* class, the *PTEST\_PYTEST\_DIR* variable represents the path within the source tree of a Python package holding the unit tests to be run with the *pytest* framework. The default value for this variable is `tests`.

For more information, see the *ptest-python-pytest* class documentation.

### ***PV***

The version of the recipe. The version is normally extracted from the recipe filename. For example, if the recipe is named `expat_2.0.1.bb`, then the default value of *PV* will be "2.0.1". *PV* is generally not overridden within a recipe unless it is building an unstable (i.e. development) version from a source code repository (e.g. Git or Subversion).

*PV* is the default value of the *PKGVS* variable.

### ***PYPI\_PACKAGE***

When inheriting the *pypi* class, specifies the PyPI package name to be built. The default value is set based upon *BPN* (stripping any "python-" or "python3-" prefix off if present), however for some packages it will need to be set explicitly if that will not match the package name (e.g. where the package name has a prefix, underscores, uppercase letters etc.)

### ***PYPI\_PACKAGE\_EXT***

When inheriting the *pypi* class, specifies the file extension to use when fetching a package from PyPI. Default is `tar.gz`.

### *PYPI\_SRC\_URI*

When inheriting the *pypi* class, specifies the full *pythonhosted* URI for fetching the package to be built. The default value is constructed based upon *PYPI\_PACKAGE*, *PYPI\_PACKAGE\_EXT*, and *PV*. Most recipes will not need to set this variable unless they are building an unstable (i.e. development) version.

### *PYTHON\_ABI*

When used by recipes that inherit the *setuptools3* class, denotes the Application Binary Interface (ABI) currently in use for Python. By default, the ABI is "m". You do not have to set this variable as the OpenEmbedded build system sets it for you.

The OpenEmbedded build system uses the ABI to construct directory names used when installing the Python headers and libraries in sysroot (e.g. `.../python3.3m/...`).

### *QA\_EMPTY\_DIRS*

Specifies a list of directories that are expected to be empty when packaging; if `empty-dirs` appears in *ERROR\_QA* or *WARN\_QA* these will be checked and an error or warning (respectively) will be produced.

The default *QA\_EMPTY\_DIRS* value is set in *insane.bbclass*.

### *QA\_EMPTY\_DIRS\_RECOMMENDATION*

Specifies a recommendation for why a directory must be empty, which will be included in the error message if a specific directory is found to contain files. Must be overridden with the directory path to match on.

If no recommendation is specified for a directory, then the default "but it is expected to be empty" will be used.

An example message shows if files were present in '/dev':

```
QA_EMPTY_DIRS_RECOMMENDATION:/dev = "but all devices must be created at runtime
↪"
```

### *QB\_CMDLINE\_IP\_SLIRP*

If *QB\_NETWORK\_DEVICE* adds more than one network interface to QEMU, usually the `ip=` Linux kernel command line argument needs to be changed accordingly. The *QB\_CMDLINE\_IP\_SLIRP* variable allows controlling this value. See the Linux kernel documentation for more details: <https://www.kernel.org/doc/Documentation/filesystems/nfs/nfsroot.txt>.

### *QB\_CMDLINE\_IP\_TAP*

This variable is similar to the *QB\_CMDLINE\_IP\_SLIRP* variable.

Use as follows:

```
QB_CMDLINE_IP_TAP = "ip=192.168.7.@CLIENT@::192.168.7.@GATEWAY@:255.255.255.
↪0::eth0"
```

Since the tap interface requires static IP configuration, *runqemu* replaces the `@CLIENT@` and `@GATEWAY@` place holders by the IP and the gateway address of the QEMU guest.

### *QB\_DEFAULT\_BIOS*

The *QB\_DEFAULT\_BIOS* variable can be used to provide a default value for the path of a file located in *DEPLOY\_DIR\_IMAGE* and used by *runqemu* to specify the `-bios` option of QEMU. For example, this variable can be set as follows to emulate U-Boot for the *qemuarm64* machine:



```
QB_DEFAULT_BIOS = "u-boot.bin"
```

The above example makes the assumption the U-Boot recipe was built and that the `u-boot.bin` is deployed in the `DEPLOY_DIR_IMAGE` directory.

**i Nota**

When using `runqemu`, the `BIOS` environment variable takes precedence over this variable.

### ***QB\_DEFAULT\_FSTYPE***

The `QB_DEFAULT_FSTYPE` variable controls the default filesystem type to boot. It is represented as the file extension of one of the root filesystem image extension found in `DEPLOY_DIR_IMAGE`. For example: `ext4`, `zst`.

### ***QB\_DEFAULT\_KERNEL***

When using `runqemu`, the `QB_DEFAULT_KERNEL` variable controls the default Linux kernel image to boot, found in `DEPLOY_DIR_IMAGE`. For example: `bzImage`.

### ***QB\_DRIVE\_TYPE***

When using `runqemu`, the `QB_DRIVE_TYPE` variable specifies the type of drive to emulate when starting the emulated machine. Valid values are:

- `/dev/hd`: emulates an IDE drive.
- `/dev/mmcblk`: emulates an SD Card.
- `/dev/sd`: emulates an SCSI drive.
- `/dev/vd`: emulates a VirtIO drive.
- `/dev/vdb`: emulates a block VirtIO drive.

### ***QB\_GRAPHICS***

When using `runqemu`, the `QB_GRAPHICS` variable controls the QEMU video card type to emulate. For example: `-vga std`.

This value is appended to the argument list when running `qemu`.

### ***QB\_KERNEL\_CMDLINE\_APPEND***

The `QB_KERNEL_CMDLINE_APPEND` variable controls the options passed to the Linux kernel's `-append` QEMU options, which controls the Linux kernel command-line.

Per esempio:

```
QB_KERNEL_CMDLINE_APPEND = "console=ttyS0"
```

### ***QB\_MEM***

The `QB_MEM` variable controls the amount of memory allocated to the emulated machine. Specify as follows:

```
QB_MEM = "-m 512"
```

### ***QB\_NETWORK\_DEVICE***

When using `runqemu`, the ***QB\_NETWORK\_DEVICE*** variable controls the network device instantiated by QEMU. This value needs to be compatible with the ***QB\_TAP\_OPT*** variable.

Example:

```
QB_NETWORK_DEVICE = "-device virtio-net-pci,netdev=net0,mac=@MAC@"
```

`runqemu` replaces `@MAC@` with a predefined mac address.

### ***QB\_NFSROOTFS\_EXTRA\_OPT***

When using `runqemu`, the ***QB\_NFSROOTFS\_EXTRA\_OPT*** variable controls extra options to be appended to the NFS rootfs options in the Linux kernel command-line.

Per esempio:

```
QB_NFSROOTFS_EXTRA_OPT = "wsize=4096,rsize=4096"
```

### ***QB\_OPT\_APPEND***

When using `runqemu`, the ***QB\_OPT\_APPEND*** variable controls general options to append to QEMU when starting.

### ***QB\_RNG***

When using `runqemu`, the ***QB\_RNG*** variable controls pass-through for host random number generator, it can speedup boot in system mode, where system is experiencing entropy starvation.

Per esempio:

```
QB_RNG = "-object rng-random,filename=/dev/urandom,id=rng0 -device virtio-rng-  
→pci,rng=rng0"
```

### ***QB\_ROOTFS\_EXTRA\_OPT***

When using `runqemu`, the ***QB\_ROOTFS\_EXTRA\_OPT*** variable controls extra options to be appended to the rootfs device options.

### ***QB\_SERIAL\_OPT***

When using `runqemu`, the ***QB\_SERIAL\_OPT*** variable controls the serial port option.

Per esempio:

```
QB_SERIAL_OPT = "--serial mon:stdio"
```

### ***QB\_SMP***

When using `runqemu`, the ***QB\_SMP*** variable controls amount of CPU cores made available inside the QEMU guest, each mapped to a thread on the host.

Per esempio:

```
QB_SMP = "-smp 8"
```

### *QB\_TAP\_NAMESERVER*

When using `runqemu`, the `QB_TAP_NAMESERVER` variable controls the default `name server` used in the QEMU guest.

### *QB\_TAP\_OPT*

When using `runqemu`, the `QB_TAP_OPT` variable controls the network option for "tap" mode.

Per esempio:

```
QB_TAP_OPT = "-netdev tap,id=net0,ifname=@TAP@,script=no,downscript=no"
```

Note that `runqemu` will replace `@TAP@` with the tap interface in use, such as `tap0`, `tap1`, etc.

### *RANLIB*

The minimal command and arguments to run `ranlib`.

### *RCONFLICTS*

The list of packages that conflict with packages. Note that packages will not be installed if conflicting packages are not first removed.

Like all package-controlling variables, you must always use them in conjunction with a package name override. Here is an example:

```
RCONFLICTS:${PN} = "another_conflicting_package_name"
```

BitBake, which the OpenEmbedded build system uses, supports specifying versioned dependencies. Although the syntax varies depending on the packaging format, BitBake hides these differences from you. Here is the general syntax to specify versions with the `RCONFLICTS` variable:

```
RCONFLICTS:${PN} = "package (operator version)"
```

For operator, you can specify the following:

- =
- <
- >
- <=
- >=

For example, the following sets up a dependency on version 1.2 or greater of the package `foo`:

```
RCONFLICTS:${PN} = "foo (>= 1.2)"
```

### *RDEPENDS*

Lists runtime dependencies of a package. These dependencies are other packages that must be installed in order for the package to function correctly. As an example, the following assignment declares that the package `foo` needs the packages `bar` and `baz` to be installed:

```
RDEPENDS:foo = "bar baz"
```

The most common types of package runtime dependencies are automatically detected and added. Therefore, most recipes do not need to set *RDEPENDS*. For more information, see the "*Dipendenze di Runtime Aggiunte Automaticamente*" section in the Yocto Project Overview and Concepts Manual.

The practical effect of the above *RDEPENDS* assignment is that `bar` and `baz` will be declared as dependencies inside the package `foo` when it is written out by one of the *do\_package\_write\_\** tasks. Exactly how this is done depends on which package format is used, which is determined by *PACKAGE\_CLASSES*. When the corresponding package manager installs the package, it will know to also install the packages on which it depends.

To ensure that the packages `bar` and `baz` get built, the previous *RDEPENDS* assignment also causes a task dependency to be added. This dependency is from the recipe's *do\_build* (not to be confused with *do\_compile*) task to the *do\_package\_write\_\** task of the recipes that build `bar` and `baz`.

The names of the packages you list within *RDEPENDS* must be the names of other packages --- they cannot be recipe names. Although package names and recipe names usually match, the important point here is that you are providing package names within the *RDEPENDS* variable. For an example of the default list of packages created from a recipe, see the *PACKAGES* variable.

Because the *RDEPENDS* variable applies to packages being built, you should always use the variable in a form with an attached package name (remember that a single recipe can build multiple packages). For example, suppose you are building a development package that depends on the `perl` package. In this case, you would use the following *RDEPENDS* statement:

```
RDEPENDS:${PN}-dev += "perl"
```

In the example, the development package depends on the `perl` package. Thus, the *RDEPENDS* variable has the `${PN}-dev` package name as part of the variable.

#### Nota

*RDEPENDS:\${PN}-dev* includes *\${PN}* by default. This default is set in the BitBake configuration file (`meta/conf/bitbake.conf`). Be careful not to accidentally remove *\${PN}* when modifying *RDEPENDS:\${PN}-dev*. Use the `+="` operator rather than the `"=` operator.

The package names you use with *RDEPENDS* must appear as they would in the *PACKAGES* variable. The *PKG* variable allows a different name to be used for the final package (e.g. the *debian* class uses this to rename packages), but this final package name cannot be used with *RDEPENDS*, which makes sense as *RDEPENDS* is meant to be independent of the package format used.

BitBake, which the OpenEmbedded build system uses, supports specifying versioned dependencies. Although the syntax varies depending on the packaging format, BitBake hides these differences from you. Here is the general syntax to specify versions with the *RDEPENDS* variable:

```
RDEPENDS:${PN} = "package (operator version)"
```

For `operator`, you can specify the following:

- `=`
- `<`
- `>`
- `<=`
- `>=`

For `version`, provide the version number.

#### **Nota**

You can use `EXTENDPKGVS` to provide a full package version specification.

For example, the following sets up a dependency on version 1.2 or greater of the package `foo`:

```
RDEPENDS:${PN} = "foo (>= 1.2) "
```

For information on build-time dependencies, see the `DEPENDS` variable. You can also see the "Tasks" and "Dependencies" sections in the BitBake User Manual for additional information on tasks and dependencies.

### **READEF**

The minimal command and arguments to run `readelf`.

### **RECIPE\_MAINTAINER**

This variable defines the name and e-mail address of the maintainer of a recipe. Such information can be used by human users submitted changes, and by automated tools to send notifications, for example about vulnerabilities or source updates.

The variable can be defined in a global distribution `maintainers.inc` file:

```
meta/conf/distro/include/maintainers.inc:RECIPE_MAINTAINER:pn-sysvinit = "Ross_
↪Burton <ross.burton@arm.com>"
```

It can also be directly defined in a recipe, for example in the `libgpiod` one:

```
RECIPE_MAINTAINER = "Bartosz Golaszewski <brgl@bgdev.pl>"
```

### **RECIPE\_NO\_UPDATE\_REASON**

If a recipe should not be replaced by a more recent upstream version, putting the reason why in this variable in a recipe allows `devtool check-upgrade-status` command to display it, as explained in the "Checking on the Upgrade Status of a Recipe" section.

### **RECIPE\_SYSROOT**

This variable points to the directory populated with all files provided by recipes specified in `DEPENDS`. As the name indicates, think of this variable as a custom root (`/`) for the recipe, that will be used by the compiler in order to find headers and other files needed to complete its job.

This variable is used to define *STAGING\_DIR\_HOST* or *STAGING\_DIR\_TARGET* according to the type of the recipe and the build target.

To better understand this variable, consider the following examples:

- For `#include <header.h>`, `header.h` should be in "`${RECIPE_SYSROOT}/usr/include`"
- For `-lexample`, `libexample.so` should be in "`${RECIPE_SYSROOT}/lib`" or other library sysroot directories.

The default value is "`${WORKDIR}/recipe-sysroot`". Do not modify it.

### *RECIPE\_SYSROOT\_NATIVE*

This is similar to *RECIPE\_SYSROOT* but files in it are provided by native recipes. This allows a recipe built for the target machine to use native tools.

This variable is used to define *STAGING\_DIR\_NATIVE*.

The default value is "`${WORKDIR}/recipe-sysroot-native`". Do not modify it.

### *RECIPE\_UPGRADE\_EXTRA\_TASKS*

When upgrading a recipe with `devtool upgrade`, the variable *RECIPE\_UPGRADE\_EXTRA\_TASKS* specifies a space-delimited list of tasks to run after the new sources have been unpacked.

For some recipes, after the new source has been unpacked, additional tasks may need to be run during an upgrade. A good example of this is recipes which inherit *cargo-update-recipe-crates*, where the *do\_update\_crates* task needs to be run whenever `Cargo.toml`/`Cargo.lock` have changed in the source.

### *REPODIR*

See *REPODIR* in the BitBake manual.

### *REQUIRED\_COMBINED\_FEATURES*

When inheriting the *features\_check* class, this variable identifies combined features (the intersection of *MACHINE\_FEATURES* and *DISTRO\_FEATURES*) that must exist in the current configuration in order for the *OpenEmbedded Build System* to build the recipe. In other words, if the *REQUIRED\_COMBINED\_FEATURES* variable lists a feature that does not appear in *COMBINED\_FEATURES* within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

### *REQUIRED\_DISTRO\_FEATURES*

When inheriting the *features\_check* class, this variable identifies distribution features that must exist in the current configuration in order for the *OpenEmbedded build system* to build the recipe. In other words, if the *REQUIRED\_DISTRO\_FEATURES* variable lists a feature that does not appear in *DISTRO\_FEATURES* within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

### *REQUIRED\_IMAGE\_FEATURES*

When inheriting the *features\_check* class, this variable identifies image features that must exist in the current configuration in order for the *OpenEmbedded Build System* to build the recipe. In other words, if the *REQUIRED\_IMAGE\_FEATURES* variable lists a feature that does not appear in *IMAGE\_FEATURES* within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

Compared to other `REQUIRED_*_FEATURES` variables, the `REQUIRED_IMAGE_FEATURES` variable only targets image recipes, as the `IMAGE_FEATURES` variable is handled by the `core-image` class). However, the `REQUIRED_IMAGE_FEATURES` variable can also be set from a *Configuration File*, such as a distro configuration file, if the list of required image features should apply to all images using this `DISTRO`.

#### **`REQUIRED_MACHINE_FEATURES`**

When inheriting the `features_check` class, this variable identifies `MACHINE_FEATURES` that must exist in the current configuration in order for the *OpenEmbedded Build System* to build the recipe. In other words, if the `REQUIRED_MACHINE_FEATURES` variable lists a feature that does not appear in `MACHINE_FEATURES` within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### **`REQUIRED_TUNE_FEATURES`**

When inheriting the `features_check` class, this variable identifies tune features that must exist in the current configuration in order for the *OpenEmbedded Build System* to build the recipe. In other words, if the `REQUIRED_TUNE_FEATURES` variable lists a feature that does not appear in `TUNE_FEATURES` within the current configuration, then the recipe will be skipped, and if the build system attempts to build the recipe then an error will be triggered.

#### **`REQUIRED_VERSION`**

If there are multiple versions of a recipe available, this variable determines which version should be given preference. `REQUIRED_VERSION` works in exactly the same manner as `PREFERRED_VERSION`, except that if the specified version is not available then an error message is shown and the build fails immediately.

If both `REQUIRED_VERSION` and `PREFERRED_VERSION` are set for the same recipe, the `REQUIRED_VERSION` value applies.

#### **`RETAIN_DIRS_ALWAYS`**

When inheriting the `retain` class, this variable holds space-separated recipe-specific directories to always save in a tarball whether the recipe build has failed or not.

#### **`RETAIN_DIRS_FAILURE`**

When inheriting the `retain` class, this variable holds space-separated recipe-specific directories to save in a tarball on failure of the recipe's build.

#### **`RETAIN_DIRS_GLOBAL_ALWAYS`**

When inheriting the `retain` class, this variable holds space-separated directories that are not specific to a recipe to save in a tarball whether the build has failed or not.

#### **`RETAIN_DIRS_GLOBAL_FAILURE`**

When inheriting the `retain` class, this variable holds space-separated directories that are not specific to a recipe to save in a tarball on build failure.

#### **`RETAIN_ENABLED`**

Disables the creation of a tarball of the work directory done by the `retain` class. Can be set to specific recipes to disable the class when the class was inherited globally with `INHERIT`.

#### **`RETAIN_IGNORE_TASKS`**

When inheriting the `retain` class, the `RETAIN_IGNORE_TASKS` variable can contain a list of tasks that should *not* trigger retention.

### ***RETAIN\_OUTDIR***

When inheriting the *retain* class, this variable specifies the directory where to save the tarball of the work directory. The default directory is `${TMPDIR}/retain`.

### ***RETAIN\_TARBALL\_SUFFIX***

When inheriting the *retain* class, this variable specifies the suffix of the tarball of the work directory. The default suffix is `${DATETIME}.tar.gz`.

### ***RM\_WORK\_EXCLUDE***

With *rm\_work* enabled, this variable specifies a list of recipes whose work directories should not be removed. See the "*rm\_work*" section for more details.

### ***RM\_WORK\_EXCLUDE\_ITEMS***

With *rm\_work* enabled, this variable specifies a list of files or folders --- relative to the recipe's *WORKDIR* --- to be preserved. See the "*rm\_work*" section for more details.

### ***ROOT\_HOME***

Defines the root home directory. By default, this directory is set as follows in the BitBake configuration file:

```
ROOT_HOME ??= "/home/root"
```

#### ***i* Nota**

This default value is likely used because some embedded solutions prefer to have a read-only root filesystem and prefer to keep writeable data in one place.

When setting `INIT_MANAGER = systemd`, the default will be set to:

```
ROOT_HOME ?= "/root"
```

You can also override the default by setting the variable in your distro configuration or in the *build/conf/local.conf* file.

### ***ROOTFS***

Indicates a filesystem image to include as the root filesystem.

The *ROOTFS* variable is an optional variable used with the *image-live* class.

### ***ROOTFS\_POSTINSTALL\_COMMAND***

Specifies a list of functions to call after the OpenEmbedded build system has installed packages. You can specify functions separated by spaces:

```
ROOTFS_POSTINSTALL_COMMAND += "function"
```

If you need to pass the root filesystem path to a command within a function, you can use `${IMAGE_ROOTFS}`, which points to the directory that becomes the root filesystem image. See the *IMAGE\_ROOTFS* variable for more information.



### *ROOTFS\_POSTPROCESS\_COMMAND*

Specifies a list of functions to call once the OpenEmbedded build system has created the root filesystem. You can specify functions separated by spaces:

```
ROOTFS_POSTPROCESS_COMMAND += "function"
```

If you need to pass the root filesystem path to a command within a function, you can use `${IMAGE_ROOTFS}`, which points to the directory that becomes the root filesystem image. See the *IMAGE\_ROOTFS* variable for more information.

### *ROOTFS\_POSTUNINSTALL\_COMMAND*

Specifies a list of functions to call after the OpenEmbedded build system has removed unnecessary packages. When runtime package management is disabled in the image, several packages are removed including `base-passwd`, `shadow`, and `update-alternatives`. You can specify functions separated by spaces:

```
ROOTFS_POSTUNINSTALL_COMMAND += "function"
```

If you need to pass the root filesystem path to a command within a function, you can use `${IMAGE_ROOTFS}`, which points to the directory that becomes the root filesystem image. See the *IMAGE\_ROOTFS* variable for more information.

### *ROOTFS\_PREPROCESS\_COMMAND*

Specifies a list of functions to call before the OpenEmbedded build system has created the root filesystem. You can specify functions separated by spaces:

```
ROOTFS_PREPROCESS_COMMAND += "function"
```

If you need to pass the root filesystem path to a command within a function, you can use `${IMAGE_ROOTFS}`, which points to the directory that becomes the root filesystem image. See the *IMAGE\_ROOTFS* variable for more information.

### *RPMBUILD\_EXTRA\_PARAMS*

Specifies extra user-defined parameters for the `rpmbuild` command.

### *RPROVIDES*

A list of package name aliases that a package also provides. These aliases are useful for satisfying runtime dependencies of other packages both during the build and on the target (as specified by *RDEPENDS*).

#### **Nota**

A package's own name is implicitly already in its *RPROVIDES* list.

As with all package-controlling variables, you must always use the variable in conjunction with a package name override. Here is an example:

```
RPROVIDES:${PN} = "widget-abi-2"
```

### *RRECOMMENDS*

A list of packages that extends the usability of a package being built. The package being built does not depend

on this list of packages in order to successfully build, but rather uses them for extended usability. To specify runtime dependencies for packages, see the [RDEPENDS](#) variable.

The package manager will automatically install the [RRECOMMENDS](#) list of packages when installing the built package. However, you can prevent listed packages from being installed by using the [BAD\\_RECOMMENDATIONS](#), [NO\\_RECOMMENDATIONS](#), and [PACKAGE\\_EXCLUDE](#) variables.

Packages specified in [RRECOMMENDS](#) need not actually be produced. However, there must be a recipe providing each package, either through the [PACKAGES](#) or [PACKAGES\\_DYNAMIC](#) variables or the [RPROVIDES](#) variable, or an error will occur during the build. If such a recipe does exist and the package is not produced, the build continues without error.

Because the [RRECOMMENDS](#) variable applies to packages being built, you should always attach an override to the variable to specify the particular package whose usability is being extended. For example, suppose you are building a development package that is extended to support wireless functionality. In this case, you would use the following:

```
RRECOMMENDS:${PN}-dev += "wireless_package_name"
```

In the example, the package name (`${PN}-dev`) must appear as it would in the [PACKAGES](#) namespace before any renaming of the output package by classes such as [debian](#).

BitBake, which the OpenEmbedded build system uses, supports specifying versioned recommends. Although the syntax varies depending on the packaging format, BitBake hides these differences from you. Here is the general syntax to specify versions with the [RRECOMMENDS](#) variable:

```
RRECOMMENDS:${PN} = "package (operator version)"
```

For `operator`, you can specify the following:

- `=`
- `<`
- `>`
- `<=`
- `>=`

For example, the following sets up a recommend on version 1.2 or greater of the package `foo`:

```
RRECOMMENDS:${PN} = "foo (>= 1.2)"
```

## [RREPLACES](#)

A list of packages replaced by a package. The package manager uses this variable to determine which package should be installed to replace other package(s) during an upgrade. In order to also have the other package(s) removed at the same time, you must add the name of the other package to the [RCONFLICTS](#) variable.

As with all package-controlling variables, you must use this variable in conjunction with a package name override. Here is an example:

```
RREPLACES:${PN} = "other_package_being_replaced"
```

BitBake, which the OpenEmbedded build system uses, supports specifying versioned replacements. Although the syntax varies depending on the packaging format, BitBake hides these differences from you. Here is the general syntax to specify versions with the *RREPLACES* variable:

```
RREPLACES:${PN} = "package (operator version) "
```

For *operator*, you can specify the following:

- =
- <
- >
- <=
- >=

For example, the following sets up a replacement using version 1.2 or greater of the package *foo*:

```
RREPLACES:${PN} = "foo (>= 1.2) "
```

### RSUGGESTS

A list of additional packages that you can suggest for installation by the package manager at the time a package is installed. Not all package managers support this functionality. This feature takes effect only when the package manager is being used to install packages on the target system from a package feed.

As with all package-controlling variables, you must always use this variable in conjunction with a package name override. Here is an example:

```
RSUGGESTS:${PN} = "useful_package another_package"
```

For more information on package management, see the *Using Runtime Package Management* section of the Yocto Project Development Tasks Manual.

### RUST\_CHANNEL

Specifies which version of Rust to build - "stable", "beta" or "nightly". The default value is "stable". Set this at your own risk, as values other than "stable" are not guaranteed to work at a given time.

### S

The location in the *Build Directory* where unpacked recipe source code resides. By default, this directory is *\${UNPACKDIR}/\${BPN}-\${PV}*, where *\${BPN}* is the base recipe name and *\${PV}* is the recipe version. If the source tarball extracts the code to a directory named anything other than *\${BPN}-\${PV}*, or if the source code is fetched from an SCM such as Git or Subversion, then you must set *S* in the recipe so that the OpenEmbedded build system knows where to find the unpacked source.

As an example, assume a *Source Directory* top-level folder named *bitbake-builds* and a default *Build Directory* at *bitbake-builds/build*. In this case, the work directory the build system uses to keep the unpacked recipe for *db* is the following:

```
bitbake-builds/build/tmp/work/qemux86-poky-linux/db/5.1.19-r3/sources/db-5.1.19
```

The unpacked source code resides in the `db-5.1.19` folder.

### ***SANITY\_REQUIRED\_UTILITIES***

Specifies a list of command-line utilities that should be checked for during the initial sanity checking process when running BitBake. If any of the utilities are not installed on the build host, then BitBake immediately exits with an error.

### ***SANITY\_TESTED\_DISTROS***

A list of the host distribution identifiers that the build system has been tested against. Identifiers consist of the host distributor ID followed by the release, as reported by the `lsb_release` tool or as read from `/etc/lsb-release`. Separate the list items with explicit newline characters (`\n`). If *SANITY\_TESTED\_DISTROS* is not empty and the current value of *NATIVE\_SBSTRING* does not appear in the list, then the build system reports a warning that indicates the current host distribution has not been tested as a build host.

### ***SBOM\_CVE\_CHECK\_EXPORT\_VARS***

When inheriting the *sbom-cve-check* class, this variable holds the list of variables that declare export files to generate.

Each variable must have a `type` and an `ext` flag set:

- The `type` flag contains the value that is passed to the `--export-type` command line argument of `sbom-cve-check`.
- The `ext` flag contains the filename extension (suffix). The output filename is going will be `${IMAGE_NAME}${ext}`.

Per esempio:

```
SBOM_CVE_CHECK_EXPORT_VARS = "SBOM_CVE_CHECK_EXPORT_SPDX3"
SBOM_CVE_CHECK_EXPORT_SPDX3[type] = "spdx3"
SBOM_CVE_CHECK_EXPORT_SPDX3[ext] = ".sbom-cve-check.spdx.json"
```

### ***SBOM\_CVE\_CHECK\_EXTRA\_ARGS***

When inheriting the *sbom-cve-check* class, this variable can be used to pass extra arguments to the `sbom-cve-check` command-line tool.

See the [documentation](#) of `sbom-cve-check` for more information.

### ***SBOM\_CVE\_CHECK\_SCAN\_SCOPE***

When inheriting the *sbom-cve-check* class, this variable controls whether to scan target and native, just target, or just native recipes.

Valid values are:

- `target` (default): recipes are scanned in their target context
- `native`: recipes are scanned in their *native* context
- `both`: recipes are scanned in both their target and *native* context

### ***SBOM\_CVE\_CHECK\_SHOW\_WARNINGS***

When inheriting the *sbom-cve-check* class, this variable controls whether to show warnings when CVEs with the Unpatched status are found. Example output:

```
WARNING: core-image-minimal-1.0-r0 do_sbom_cve_check: glibc-2.43+git: Found_
→unpatched CVEs: CVE-2010-4756
```

Set to "1" to show the warnings, "0" otherwise.

See *Verifica delle Vulnerabilità* for more information.

### ***SDK\_ARCH***

The target architecture for the SDK. Typically, you do not directly set this variable. Instead, use *SDKMACHINE*.

### ***SDK\_ARCHIVE\_TYPE***

Specifies the type of archive to create for the SDK. Valid values:

- tar.xz (default)
- tar.zst
- 7zip
- zip

Only one archive type can be specified.

### ***SDK\_AS\_ARCH***

Specifies architecture-specific assembler flags when building *nativesdk* recipes. By default, the value of *SDK\_AS\_ARCH* equals the one of *BUILD\_AS\_ARCH*.

### ***SDK\_BUILDINFO\_FILE***

When using the *image-buildinfo* class, specifies the file in the SDK to write the build information into. The default value is `"/buildinfo"`.

### ***SDK\_CC\_ARCH***

Specifies the architecture-specific C compiler flags when building *nativesdk* recipes. By default, the value of *SDK\_CC\_ARCH* equals the one of *BUILD\_CC\_ARCH*.

### ***SDK\_CUSTOM\_TEMPLATECONF***

When building the extensible SDK, if *SDK\_CUSTOM\_TEMPLATECONF* is set to "1" and a `conf/templateconf.cfg` file exists in the *Build Directory* (*TOPDIR*) then this will be copied into the SDK.

### ***SDK\_DEPLOY***

The directory set up and used by the *populate\_sdk\_base* class to which the SDK is deployed. The *populate\_sdk\_base* class defines *SDK\_DEPLOY* as follows:

```
SDK_DEPLOY = "${TMPDIR}/deploy/sdk"
```

### ***SDK\_DIR***

The parent directory used by the OpenEmbedded build system when creating SDK output. The *populate\_sdk\_base* class defines the variable as follows:

```
SDK_DIR = "${WORKDIR}/sdk"
```

**i Nota**

The *SDK\_DIR* directory is a temporary directory as it is part of *WORKDIR*. The final output directory is *SDK\_DEPLOY*.

**SDK\_EXT\_TYPE**

Controls whether or not shared state artifacts are copied into the extensible SDK. The default value of "full" copies all of the required shared state artifacts into the extensible SDK. The value "minimal" leaves these artifacts out of the SDK.

**i Nota**

If you set the variable to "minimal", you need to ensure *SSTATE\_MIRRORS* is set in the SDK's configuration to enable the artifacts to be fetched as needed.

**SDK\_FEATURES**

The *SDK\_FEATURES* variable defines the list of features to include in a *standard SDK* or *extensible SDK*, resolved when running the *do\_populate\_sdk* or *do\_populate\_sdk\_ext* task. This variable is analogous to *IMAGE\_FEATURES*, but for the SDK instead of the image.

For a full list of features, see the *SDK Features* section.

**SDK\_HOST\_MANIFEST**

The manifest file for the host part of the SDK. This file lists all the installed packages that make up the host part of the SDK. The file contains package information on a line-per-package basis as follows:

```
packagename packagearch version
```

The *populate\_sdk\_base* class defines the manifest file as follows:

```
SDK_HOST_MANIFEST = "${SDK_DEPLOY}/${TOOLCHAIN_OUTPUTNAME}.host.manifest"
```

The location is derived using the *SDK\_DEPLOY* and *TOOLCHAIN\_OUTPUTNAME* variables.

**SDK\_INCLUDE\_PKGDATA**

When set to "1", specifies to include the packagedata for all recipes in the "world" target in the extensible SDK. Including this data allows the `devtool search` command to find these recipes in search results, as well as allows the `devtool add` command to map dependencies more effectively.

**i Nota**

Enabling the `SDK_INCLUDE_PKGDATA` variable significantly increases build time because all of world needs to be built. Enabling the variable also slightly increases the size of the extensible SDK.

**`SDK_INCLUDE_TOOLCHAIN`**

When set to "1", specifies to include the toolchain in the extensible SDK. Including the toolchain is useful particularly when `SDK_EXT_TYPE` is set to "minimal" to keep the SDK reasonably small but you still want to provide a usable toolchain. For example, suppose you want to use the toolchain from an IDE or from other tools and you do not want to perform additional steps to install the toolchain.

The `SDK_INCLUDE_TOOLCHAIN` variable defaults to "0" if `SDK_EXT_TYPE` is set to "minimal", and defaults to "1" if `SDK_EXT_TYPE` is set to "full".

**`SDK_LD_ARCH`**

Specifies architecture-specific linker flags when building *nativesdk* recipes. By default, the value of `SDK_LD_ARCH` equals the one of `BUILD_LD_ARCH`.

**`SDK_NAME`**

The base name for SDK output files. The default value (as set in `meta-poky/conf/distro/poky.conf`) is derived from the `DISTRO`, `TCLIBC`, `SDKMACHINE`, `IMAGE_BASENAME`, `TUNE_PKGARCH`, and `MACHINE` variables:

```
SDK_NAME = "${DISTRO}-${TCLIBC}-${SDKMACHINE}-${IMAGE_BASENAME}-${TUNE_PKGARCH}
→-${MACHINE}"
```

**`SDK_OS`**

Specifies the operating system for which the SDK will be built. The default value is the value of `BUILD_OS`.

**`SDK_OUTPUT`**

The location used by the OpenEmbedded build system when creating SDK output. The *populate\_sdk\_base* class defines the variable as follows:

```
SDK_DIR = "${WORKDIR}/sdk"
SDK_OUTPUT = "${SDK_DIR}/image"
SDK_DEPLOY = "${DEPLOY_DIR}/sdk"
```

**i Nota**

The `SDK_OUTPUT` directory is a temporary directory as it is part of `WORKDIR` by way of `SDK_DIR`. The final output directory is `SDK_DEPLOY`.

**`SDK_PACKAGE_ARCHS`**

Specifies a list of architectures compatible with the SDK machine. This variable is set automatically and should not normally be hand-edited. Entries are separated using spaces and listed in order of priority. The default value for `SDK_PACKAGE_ARCHS` is "all any noarch \${SDK\_ARCH}-\${SDKPKGSUFFIX}".

### *SDK\_POSTPROCESS\_COMMAND*

Specifies a list of functions to call once the OpenEmbedded build system creates the SDK. You can specify functions separated by spaces:

```
SDK_POSTPROCESS_COMMAND += "function"
```

If you need to pass an SDK path to a command within a function, you can use `${SDK_DIR}`, which points to the parent directory used by the OpenEmbedded build system when creating SDK output. See the [SDK\\_DIR](#) variable for more information.

### *SDK\_PREFIX*

The toolchain binary prefix used for *nativesdk* recipes. The OpenEmbedded build system uses the [SDK\\_PREFIX](#) value to set the [TARGET\\_PREFIX](#) when building *nativesdk* recipes. The default value is `"${SDK_SYS}-"`.

### *SDK\_RECRDEP\_TASKS*

A list of shared state tasks added to the extensible SDK. By default, the following tasks are added:

- *do\_populate\_lic*
- *do\_package\_qa*
- *do\_populate\_sysroot*
- *do\_deploy*

Despite the default value of `""` for the [SDK\\_RECRDEP\\_TASKS](#) variable, the above four tasks are always added to the SDK. To specify tasks beyond these four, you need to use the [SDK\\_RECRDEP\\_TASKS](#) variable (e.g. you are defining additional tasks that are needed in order to build [SDK\\_TARGETS](#)).

### *SDK\_SYS*

Specifies the system, including the architecture and the operating system, for which the SDK will be built.

The OpenEmbedded build system automatically sets this variable based on [SDK\\_ARCH](#), [SDK\\_VENDOR](#), and [SDK\\_OS](#). You do not need to set the [SDK\\_SYS](#) variable yourself.

### *SDK\_TARGET\_MANIFEST*

The manifest file for the target part of the SDK. This file lists all the installed packages that make up the target part of the SDK. The file contains package information on a line-per-package basis as follows:

```
packagename packagearch version
```

The *populate\_sdk\_base* class defines the manifest file as follows:

```
SDK_TARGET_MANIFEST = "${SDK_DEPLOY}/${TOOLCHAIN_OUTPUTNAME}.target.manifest"
```

The location is derived using the [SDK\\_DEPLOY](#) and [TOOLCHAIN\\_OUTPUTNAME](#) variables.

### *SDK\_TARGETS*

A list of targets to install from shared state as part of the standard or extensible SDK installation. The default value is `"${PN}"` (i.e. the image from which the SDK is built).

The [SDK\\_TARGETS](#) variable is an internal variable and typically would not be changed.



### SDK\_TITLE

The title to be printed when running the SDK installer. By default, this title is based on the *DISTRO\_NAME* or *DISTRO* variable and is set in the *populate\_sdk\_base* class as follows:

```
SDK_TITLE ??= "${@d.getVar('DISTRO_NAME') or d.getVar('DISTRO')} SDK"
```

For the *poky* reference distribution, *SDK\_TITLE* is set to "Poky (Yocto Project Reference Distro)".

For information on how to change this default title, see the "*Changing the Extensible SDK Installer Title*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### SDK\_UPDATE\_URL

An optional URL for an update server for the extensible SDK. If set, the value is used as the default update server when running `devtool sdk-update` within the extensible SDK.

### SDK\_VENDOR

Specifies the name of the SDK vendor.

### SDK\_VERSION

Specifies the version of the SDK. The Poky distribution configuration file (`/meta-poky/conf/distro/poky.conf`) sets the default *SDK\_VERSION* as follows:

```
SDK_VERSION = "${@d.getVar('DISTRO_VERSION')}.replace('snapshot-${METADATA_
→REVISION}', 'snapshot')}"
```

For additional information, see the *DISTRO\_VERSION* and *METADATA\_REVISION* variables.

### SDK\_ZIP\_OPTIONS

Specifies extra options to pass to the `zip` command when zipping the SDK (i.e. when *SDK\_ARCHIVE\_TYPE* is set to "zip"). The default value is "-y".

### SDKEXTPATH

The default installation directory for the Extensible SDK. By default, this directory is based on the *DISTRO* variable and is set in the *populate\_sdk\_base* class as follows:

```
SDKEXTPATH ??= "~/${@d.getVar('DISTRO')}_sdk"
```

For the *Poky* reference distro, the *SDKEXTPATH* is set to "poky\_sdk".

For information on how to change this default directory, see the "*Changing the Default SDK Installation Directory*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### SDKIMAGE\_FEATURES

Equivalent to *IMAGE\_FEATURES*. However, this variable applies to the SDK generated from an image using the following command:

```
$ bitbake -c populate_sdk imagename
```

### SDKMACHINE

The machine for which the SDK is built. In other words, the SDK is built such that it runs on the target

you specify with the *SDKMACHINE* value. The value points to a corresponding `.conf` file under `conf/machine-sdk/` in the enabled layers, for example `aarch64`, `i586`, `i686`, `ppc64`, `ppc64le`, and `x86_64` are available in `OpenEmbedded-Core`.

The variable defaults to *BUILD\_ARCH* so that SDKs are built for the architecture of the build machine.

**i Nota**

You cannot set the *SDKMACHINE* variable in your distribution configuration file. If you do, the configuration will not take effect.

### *SDKPATH*

Defines the path used to collect the SDK components and build the installer.

### *SDKPATHINSTALL*

Defines the path offered to the user for installation of the SDK that is generated by the OpenEmbedded build system. The path appears as the default location for installing the SDK when you run the SDK's installation script. You can override the offered path when you run the script.

### *SDKTARGETSYSROOT*

The full path to the sysroot used for cross-compilation within an SDK as it will be when installed into the default *SDKPATHINSTALL*.

### *SECTION*

The section in which packages should be categorized. Package management utilities can make use of this variable.

### *SELECTED\_OPTIMIZATION*

Specifies the optimization flags passed to the C compiler when building for the target. The flags are passed through the default value of the *TARGET\_CFLAGS* variable.

The *SELECTED\_OPTIMIZATION* variable takes the value of *FULL\_OPTIMIZATION* unless *DEBUG\_BUILD* = "1", in which case the value of *DEBUG\_OPTIMIZATION* is used.

### *SERIAL\_CONSOLES*

Defines a serial console (TTY) to enable using `getty`. Provide a value that specifies the baud rate followed by the TTY device name separated by a semicolon. Use spaces to separate multiple devices:

```
SERIAL_CONSOLES = "115200;ttyS0 115200;ttyS1"
```

### *SETUPTOOLS\_BUILD\_ARGS*

When used by recipes that inherit the *setuptools3* class, this variable can be used to specify additional arguments to be passed to `setup.py build` in the `setuptools3_do_compile()` task.

### *SETUPTOOLS\_SETUP\_PATH*

When used by recipes that inherit the *setuptools3* class, this variable should be used to specify the directory in which the `setup.py` file is located if it is not at the root of the source tree (as specified by *S*). For example, in a recipe where the sources are fetched from a Git repository and `setup.py` is in a `python/pythonmodule` subdirectory, you would have this:

```
SETUPTOOLS_SETUP_PATH = "${S}/python/pythonmodule"
```

### *SIGGEN\_EXCLUDE\_SAFE\_RECIPE\_DEPS*

A list of recipe dependencies that should not be used to determine signatures of tasks from one recipe when they depend on tasks from another recipe. For example:

```
SIGGEN_EXCLUDE_SAFE_RECIPE_DEPS += "intone->mplayer2"
```

In the previous example, `intone` depends on `mplayer2`.

You can use the special token `"*"` on the left-hand side of the dependency to match all recipes except the one on the right-hand side. Here is an example:

```
SIGGEN_EXCLUDE_SAFE_RECIPE_DEPS += "*->quilt-native"
```

In the previous example, all recipes except `quilt-native` ignore task signatures from the `quilt-native` recipe when determining their task signatures.

Use of this variable is one mechanism to remove dependencies that affect task signatures and thus force rebuilds when a recipe changes.

#### **i** Nota

If you add an inappropriate dependency for a recipe relationship, the software might break during runtime if the interface of the second recipe was changed after the first recipe had been built.

### *SIGGEN\_EXCLUDE\_RECIPES\_ABISAFE*

A list of recipes that are completely stable and will never change. The ABI for the recipes in the list are presented by output from the tasks run to build the recipe. Use of this variable is one way to remove dependencies from one recipe on another that affect task signatures and thus force rebuilds when the recipe changes.

#### **i** Nota

If you add an inappropriate variable to this list, the software might break at runtime if the interface of the recipe was changed after the other had been built.

### *SIGGEN\_LOCKEDSIGS*

The list of locked tasks, with the form:

```
SIGGEN_LOCKEDSIGS += "<package>:<task>:<signature>"
```

If `<signature>` exists for the specified `<task>` and `<package>` in the sstate cache, BitBake will use the cached output instead of rebuilding the `<task>`. If it does not exist, BitBake will build the `<task>` and the sstate cache will be used next time.

Example:

```
SIGGEN_LOCKEDSIGS += "bc:do_
↳compile:09772aa4532512baf96d433484f27234d4b7c11dd9cda0d6f56fa1b7ce6f25f0"
```

You can obtain the signature of all the tasks for the recipe `bc` using:

```
bitbake -S none bc
```

Then you can look at files in `build/tmp/stamps/<arch>/bc` and look for files like: `<PV>.do_compile.sigdata.09772aa4532512baf96d433484f27234d4b7c11dd9cda0d6f56fa1b7ce6f25f0`.

Alternatively, you can also use *bblock* to generate this line for you.

### ***SIGGEN\_LOCKEDSIGS\_TASKSIG\_CHECK***

Specifies the debug level of task signature check. 3 levels are supported:

- `info`: displays a "Note" message to remind the user that a task is locked and the current signature matches the locked one.
- `warn`: displays a "Warning" message if a task is locked and the current signature does not match the locked one.
- `error`: same as `warn` but displays an "Error" message and aborts.

### ***SIGGEN\_LOCKEDSIGS\_TYPES***

Allowed overrides for *SIGGEN\_LOCKEDSIGS*. This is mainly used for architecture specific locks. A common value for *SIGGEN\_LOCKEDSIGS\_TYPES* is `${PACKAGE_ARCHS}`:

```
SIGGEN_LOCKEDSIGS_TYPES += "${PACKAGE_ARCHS}"

SIGGEN_LOCKEDSIGS_core2-64 += "bc:do_
↳compile:09772aa4532512baf96d433484f27234d4b7c11dd9cda0d6f56fa1b7ce6f25f0"
SIGGEN_LOCKEDSIGS_cortexa57 += "bc:do_
↳compile:12178eb6d55ef602a8fe638e49862fd247e07b228f0f08967697b655bfe4bb61"
```

Here, the `do_compile` task from `bc` will be locked only for `core2-64` and `cortexa57` but not for other architectures such as `mips32r2`.

### ***SITEINFO\_BITS***

Specifies the number of bits for the target system CPU. The value should be either "32" or "64".

### ***SITEINFO\_ENDIANNESS***

Specifies the endian byte order of the target system. The value should be either "le" for little-endian or "be" for big-endian.

### ***SKIP\_FILEDEPS***

Enables removal of all files from the "Provides" section of an RPM package. Removal of these files is required for packages containing prebuilt binaries and libraries such as `libstdc++` and `glibc`.

To enable file removal, set the variable to "1" in a *configuration file*:

```
SKIP_FILEDEPS = "1"
```

### SKIP\_RECIPE

Used to prevent the OpenEmbedded build system from building a given recipe. Specify the *PN* value as a variable flag (*varflag*) and provide a reason, which will be reported when attempting to build the recipe.

To prevent a recipe from being built, use the *SKIP\_RECIPE* variable in your *build/conf/local.conf* file or distribution configuration. Here is an example which prevents *myrecipe* from being built:

```
SKIP_RECIPE[myrecipe] = "Not supported by our organization."
```

### SOC\_FAMILY

A colon-separated list grouping together machines based upon the same family of SoC (System On Chip). You typically set this variable in a common *.inc* file that you include in the configuration files of all the machines.

#### Nota

You must include *conf/machine/include/soc-family.inc* for this variable to appear in *MACHINEOVERRIDES*.

### SOLIBS

Defines the suffix for shared libraries used on the target platform. By default, this suffix is ".so.\*" for all Linux-based systems and is defined in the *meta/conf/bitbake.conf* configuration file.

You will see this variable referenced in the default values of *FILES:\${PN}*.

### SOLIBSDEV

Defines the suffix for the development symbolic link (symlink) for shared libraries on the target platform. By default, this suffix is ".so" for Linux-based systems and is defined in the *meta/conf/bitbake.conf* configuration file.

You will see this variable referenced in the default values of *FILES:\${PN}-dev*.

### SOURCE\_DATE\_EPOCH

This defines a date expressed in number of seconds since the UNIX EPOCH (01 Jan 1970 00:00:00 UTC), which is used by multiple build systems to force a timestamp in built binaries. Many upstream projects already support this variable.

You will find more details in the [official specifications](#).

A value for each recipe is computed from the sources by *meta/lib/oe/reproducible.py*.

If a recipe wishes to override the default behavior, it should set its own *SOURCE\_DATE\_EPOCH* value:

```
SOURCE_DATE_EPOCH = "1613559011"
```

### SOURCE\_MIRROR\_FETCH

When you are fetching files to create a mirror of sources (i.e. creating a source mirror), setting *SOURCE\_MIRROR\_FETCH* to "1" in a *configuration file* ensures the source for all recipes are fetched regardless of whether or not a recipe is compatible with the configuration. A recipe is considered incompatible

with the currently configured machine when either or both the *COMPATIBLE\_MACHINE* variable and *COMPATIBLE\_HOST* variables specify compatibility with a machine other than that of the current machine or host.

**i** Nota

Do not set the *SOURCE\_MIRROR\_FETCH* variable unless you are creating a source mirror. In other words, do not set the variable during a normal build.

### *SOURCE\_MIRROR\_URL*

Defines your own *PREMIRRORS* from which to first fetch source before attempting to fetch from the upstream specified in *SRC\_URI*.

To use this variable, you must globally inherit the *own-mirrors* class and then provide the URL to your mirrors. Here is the general syntax:

```
INHERIT += "own-mirrors"
SOURCE_MIRROR_URL = "http://example.com/my_source_mirror"
```

**i** Nota

You can specify only a single URL in *SOURCE\_MIRROR\_URL*.

**i** Nota

If the mirror is protected behind a username and password, the *build host* needs to be configured so the *build system* is able to fetch from the mirror.

The recommended way to do that is by setting the following parameters in *\$HOME/.netrc* (*\$HOME* being the *build host* home directory):

```
machine example.com
login <user>
password <password>
```

This file requires permissions set to 400 or 600 to prevent other users from reading the file:

```
chmod 600 "$HOME/.netrc"
```

Another method to configure the username and password is from the URL in *SOURCE\_MIRROR\_URL* directly, with the *user* and *pswd* parameters:

```
SOURCE_MIRROR_URL = "http://example.com/my_source_mirror;user=<user>;pswd=
↵<password>"
```

### *SPDX\_AUTHORS*

This variable is used to list the authors of the created SPDX data. It works slightly differently than the other

agent variables (like *SPDX\_IMAGE\_SUPPLIER*) in that the base variable provides a list of suffixes which are used to construct the variable prefixes for the created authors. For example:

```
SPDX_AUTHORS = "myorg myself"
SPDX_AUTHORS_myorg_name = "My Organization"
SPDX_AUTHORS_myorg_type = "organization"
SPDX_AUTHORS_myself_name = "My Name"
SPDX_AUTHORS_myself_type = "Person"
```

Note that references to other objects can be made using the *\_ref* suffix, for example:

```
SPDX_AUTHORS_myself_ref = "SPDX_IMAGE_SUPPLIER"
```

And other variables can reference authors by using the correct prefix:

```
SPDX_IMAGE_SUPPLIER_ref = "SPDX_AUTHORS_myorg"
```

### *SPDX\_BUILD\_HOST*

The base variable name describing the build host on which the build is running. The value must name a key from *SPDX\_IMPORTS*, allowing the generated SPDX to reference externally defined host identity data.

Requires *SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD* to be set to "1".

#### **Avvertimento**

Setting this variable will result in non-reproducible SPDX output, because the build host identity may vary across builds.

See also *SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD*, *SPDX\_IMPORTS*, *SPDX\_INVOKED\_BY*, and *SPDX\_ON\_BEHALF\_OF*.

### *SPDX\_CONCLUDED\_LICENSE*

The *SPDX\_CONCLUDED\_LICENSE* variable allows overriding the *hasConcludedLicense* object to individual SBOM packages. This can be used when the license of a package was determined to be different than the original license string value, after analysis.

This variable can be set in two ways:

- For the entire recipe:

```
SPDX_CONCLUDED_LICENSE = "MIT & Apache-2.0"
```

- For an individual package produced by the recipe:

```
SPDX_CONCLUDED_LICENSE:${PN} = "MIT & Apache-2.0"
```

### *SPDX\_CUSTOM\_ANNOTATION\_VARS*

This option allows to associate *SPDX annotations* to a recipe, using the values of variables in the recipe:

```
ANNOTATION1 = "First annotation for recipe"
ANNOTATION2 = "Second annotation for recipe"
SPDX_CUSTOM_ANNOTATION_VARS = "ANNOTATION1 ANNOTATION2"
```

This will add a new block to the recipe `.sdp.json` output:

```
"annotations": [
  {
    "annotationDate": "2023-04-18T08:32:12Z",
    "annotationType": "OTHER",
    "annotator": "Tool: oe-spdx-creator - 1.0",
    "comment": "ANNOTATION1=First annotation for recipe"
  },
  {
    "annotationDate": "2023-04-18T08:32:12Z",
    "annotationType": "OTHER",
    "annotator": "Tool: oe-spdx-creator - 1.0",
    "comment": "ANNOTATION2=Second annotation for recipe"
  }
],
```

### ***SPDX\_FILE\_EXCLUDE\_PATTERNS***

A space-separated list of Python regular expressions used to exclude files from the SPDX output when *SPDX\_INCLUDE\_SOURCES* is enabled. Files whose paths match any of the patterns, via `re.search()`, are filtered out from the generated SBOM.

By default this variable is empty, meaning no files are excluded.

Example usage:

```
SPDX_FILE_EXCLUDE_PATTERNS = "\\*.patch$ \\*.diff$ /test/ \\*.pyc$ \\*.o$"
```

See also *SPDX\_INCLUDE\_SOURCES*.

### ***SPDX\_GIT\_PURL\_MAPPINGS***

A space-separated list of `domain:purl_type` mappings to configure PURL (Package URLs) generation for Git source downloads.

For example, adding `gitlab.example.com:pkg:gitlab` to this variable will map repositories hosted on "gitlab.example.com" to the `pkg:gitlab` PURL type.

See also the *SPDX\_PACKAGE\_URLS* variable for more information on PURLs.

### ***SPDX\_IMAGE\_SUPPLIER***

The variable prefix for describing the organization or person who supplies the image SBOM. When set, the supplier is attached to all root elements of the image SBOM using the `suppliedBy` property.

The value of this variable is the base prefix used to look up the agent's details. The following sub-variables are read using that prefix:



- `SPDX_IMAGE_SUPPLIER_name`: display name of the supplier (required)
- `SPDX_IMAGE_SUPPLIER_type`: agent type: organization, person, software, or agent (optional, defaults to agent)
- `SPDX_IMAGE_SUPPLIER_comment`: free-text comment (optional)
- `SPDX_IMAGE_SUPPLIER_id_email`: contact e-mail address (optional)

Example (set in the image recipe or in a *configuration file*):

```
SPDX_IMAGE_SUPPLIER_name = "Acme Corp"
SPDX_IMAGE_SUPPLIER_type = "organization"
```

Alternatively, it is also possible to reference an agent created by another variable prefix, using `SPDX_IMAGE_SUPPLIER_ref`. For example:

```
SPDX_IMAGE_SUPPLIER_ref = "SPDX_PACKAGE_SUPPLIER"
```

See also `SPDX_PACKAGE_SUPPLIER` and `SPDX_SDK_SUPPLIER`.

### ***SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD***

When set to "1", the SPDX output will include a `Build` object representing the parent *BitBake* invocation. This allows consumers of the SBOM to trace which CI/CD job or orchestration system triggered the build.

This variable is required for `SPDX_INVOKED_BY`, `SPDX_ON_BEHALF_OF`, and `SPDX_BUILD_HOST` to have any effect.

#### **⚠ Avvertimento**

Enabling this variable will result in non-reproducible SPDX output, because the build invocation identity changes with every run.

Enable as follows:

```
SPDX_INCLUDE_BITBAKE_PARENT_BUILD = "1"
```

See also `SPDX_BUILD_HOST`, `SPDX_INVOKED_BY`, and `SPDX_ON_BEHALF_OF`.

### ***SPDX\_INCLUDE\_COMPILED\_SOURCES***

This option allows the same as `SPDX_INCLUDE_SOURCES` but including only the sources used to compile the host tools and the target packages. While `SPDX_INCLUDE_SOURCES` includes all files in the source directory as source file descriptions, `SPDX_INCLUDE_COMPILED_SOURCES` includes only the sources that are used to produce the binaries delivered as packages. The source files that are not used during compilation are not included in the SBOM. It uses debugsource information generated during `do_package` to filter out source files.

This enables an external tool to use the SPDX information to disregard vulnerabilities that are not compiled in the packages.

Enable this option as follows:

```
SPDX_INCLUDE_COMPILED_SOURCES = "1"
```

For SPDX 2.2 format (release 4.1 "langdale"), building `core-image-minimal` for the `qemux86-64` machine, this option reduced the size of the `tmp/deploy/spdx` directory from 2GB to 1.6GB compared to `SPDX_INCLUDE_SOURCES`, as it includes only compiled objects without original source files.

With SPDX 3.0.1 JSON format, enabling this option includes both compiled sources and original source files (same as `SPDX_INCLUDE_SOURCES = "1"`), which significantly increases the SBOM size. For example, with `core-image-minimal` on `qemux86-64`, the uncompressed SBOM file can grow from hundreds of megabytes to several gigabytes.

### `SPDX_INCLUDE_KERNEL_CONFIG`

This option allows exporting the Linux kernel configuration (the contents of the `.config` file) into the recipe's SPDX document as a separate `build_Build` object. Each kernel configuration parameter (`CONFIG_*`) is recorded and linked to the main kernel object using an `ancestorOf` relationship.

#### Nota

This variable only has effect when using the SPDX 3.0 output format (see [create-spdx](#)).

Enable this option as follows:

```
SPDX_INCLUDE_KERNEL_CONFIG = "1"
```

When enabled, a separate SPDX object is created for the kernel configuration, improving reproducibility, compliance tracking, and auditing of build-time kernel features.

### `SPDX_INCLUDE_PACKAGECONFIG`

This option allows exporting a recipe's `PACKAGECONFIG` features into the recipe's SPDX document. Each feature is recorded as a `DictionaryEntry` with key `PACKAGECONFIG:<feature>` and value `enabled` or `disabled`, depending on whether the feature is active in the current build.

#### Nota

This variable only has effect when using the SPDX 3.0 output format (see [create-spdx](#)).

Enable this option as follows:

```
SPDX_INCLUDE_PACKAGECONFIG = "1"
```

When enabled, the build-time configuration of each recipe is captured in the SPDX document, improving transparency, reproducibility, and security auditing. It allows consumers of the SPDX SBOM to determine which optional features were enabled or disabled in a given build.

### `SPDX_INCLUDE_SOURCES`

This option allows to add a description of the source files used to build the host tools and the target packages, to the `spdx.json` files in `tmp/deploy/spdx/MACHINE/recipes/` under the [Build Directo-](#)

ry. As a consequence, the `spdx.json` files under the `by-namespace` and `packages` subdirectories in `tmp/deploy/spdx/MACHINE` are also modified to include references to such source file descriptions.

Enable this option as follows:

```
SPDX_INCLUDE_SOURCES = "1"
```

For SPDX 2.2 format (release 4.1 "langdale"), building `core-image-minimal` for the `qemux86-64` machine, enabling this option multiplied the total size of the `tmp/deploy/spdx` directory by a factor of 3 (+291 MiB for this image), and the size of the `IMAGE-MACHINE.spdx.tar.zst` in `tmp/deploy/images/MACHINE` by a factor of 130 (+15 MiB for this image), compared to just using the `create-spdx` class with no option.

With SPDX 3.0.1 JSON format, including source files significantly increases the SBOM size (potentially by several gigabytes for typical images).

### *SPDX\_INCLUDE\_VEX*

This option controls what **VEX** information will be present in the output SPDX documents.

It can take three different values:

- `none`: disable all VEX data.
- `current` (default): include VEX data for vulnerabilities not already fixed in the upstream source code.
- `all`: get all known historical vulnerabilities, including those already fixed upstream (warning: this can be large and slow).

### *SPDX\_INVOKED\_BY*

The variable prefix describing the agent that invoked the build. Each `Build` object in the SPDX output is linked to this agent with an `invokedBy` relationship. Requires *SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD* to be set to "1".

The sub-variables follow the same agent prefix convention as *SPDX\_IMAGE\_SUPPLIER*:

- `SPDX_INVOKED_BY_name`: display name of the invoking agent
- `SPDX_INVOKED_BY_type`: agent type, such as `software` for a CI system

Example (CI pipeline invoking the build):

```
SPDX_INCLUDE_BITBAKE_PARENT_BUILD = "1"
SPDX_INVOKED_BY_name = "GitLab CI"
SPDX_INVOKED_BY_type = "software"
```

#### **Avvertimento**

Setting this variable will likely result in non-reproducible SPDX output, because the invoking agent identity varies across builds.

See also *SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD*, *SPDX\_ON\_BEHALF\_OF*, and *SPDX\_BUILD\_HOST*.

### *SPDX\_LICENSES*

Path to the JSON file containing SPDX license identifier mappings. This file maps common license names to official SPDX license identifiers used during SBOM generation.

The default value points to a copy of the license mappings defined by SPDX (<https://github.com/spdx/license-list-data>) stored in *OpenEmbedded-Core (OE-Core)*.

You can override this variable to use a custom license mapping file if your organization uses different license naming conventions.

### *SPDX\_MULTILIB\_SSTATE\_ARCHS*

The list of sstate architectures to consider when collecting SPDX dependencies. This includes multilib architectures when multilib is enabled.

The default value is set to the value of `SSTATE_ARCHS`.

This variable is used internally by the SPDX generation classes to ensure all relevant dependencies are included in the SBOM, regardless of whether multilib is enabled or not.

### *SPDX\_NAMESPACE\_PREFIX*

This option could be used in order to change the prefix of `spdxDocument` and the prefix of `documentNamespace`. It is set by default to `http://spdx.org/spdxdoc`.

### *SPDX\_ON\_BEHALF\_OF*

The variable prefix describing the agent on whose behalf the invoking agent (*SPDX\_INVOKED\_BY*) is running the build. Requires *SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD* to be set to "1". Has no effect if *SPDX\_INVOKED\_BY* is not also set.

The sub-variables follow the same agent prefix convention as *SPDX\_IMAGE\_SUPPLIER*:

- *SPDX\_ON\_BEHALF\_OF\_name*: display name of the commissioning agent
- *SPDX\_ON\_BEHALF\_OF\_type*: agent type, such as `organization`

Example (CI system building on behalf of a customer organization):

```
SPDX_INCLUDE_BITBAKE_PARENT_BUILD = "1"
SPDX_INVOKED_BY_name = "GitLab CI"
SPDX_INVOKED_BY_type = "software"
SPDX_ON_BEHALF_OF_name = "Acme Corp"
SPDX_ON_BEHALF_OF_type = "organization"
```

#### **Avvertimento**

Setting this variable will likely result in non-reproducible SPDX output, because the agent identity varies across builds.

See also *SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD*, *SPDX\_INVOKED\_BY*, and *SPDX\_BUILD\_HOST*.

### *SPDX\_PACKAGE\_SUPPLIER*

The variable prefix describing the agent who supplies the artifacts produced by the build. Works identically to *SPDX\_IMAGE\_SUPPLIER* but applies to individual packages rather than the image SBOM.

Typically set in a distro *configuration file* to apply globally to all packages, or in a specific software recipe (or a `.bbappend`) to apply only to packages of that recipe. Recipe-level overrides (`SPDX_PACKAGE_SUPPLIER:pn-<recipe>`) are also supported:

```
SPDX_PACKAGE_SUPPLIER_name = "Acme Corp"
SPDX_PACKAGE_SUPPLIER_type = "organization"
```

See also *SPDX\_IMAGE\_SUPPLIER* and *SPDX\_SDK\_SUPPLIER*.

### *SPDX\_PACKAGE\_URL*

Provides a place for the SPDX data creator to record the package URL string (`software_packageUrl`), in accordance with the Package URL specification) for a software Package. The default value of this variable is an empty string.

### *SPDX\_PACKAGE\_URLS*

A space-separated list of Package URLs ("PURLs") for the software package. The first item in this list will be listed as the `packageUrl` property of the packages, and all PURLs (including the first one) will be listed as external references. The default value is an auto-generated `pkg:yocto` PURL based on the recipe name, version, and layer name. Override this variable to replace the default, otherwise append or prepend to add additional PURLs.

### *SPDX\_PACKAGE\_VERSION*

This variable controls the package version as seen in the SPDX 3.0 JSON output (`software_packageVersion`). The default value for this variable is *PV*.

### *SPDX\_PRETTY*

This option makes the SPDX output more human-readable, using indentation and newlines, instead of the default output in a single line:

```
SPDX_PRETTY = "1"
```

The generated SPDX files are approximately 20% bigger, but this option is recommended if you want to inspect the SPDX output files with a text editor.

### *SPDX\_SDK\_SUPPLIER*

The base variable name describing the agent who supplies the SDK SBOM. When set, the supplier is attached to all root elements of the SDK SBOM using the `suppliedBy` property.

Works identically to *SPDX\_IMAGE\_SUPPLIER* but applies to SDK builds. This includes image-based SDKs produced by `bitbake <image> -c populate_sdk` as well as toolchain SDKs produced by `bitbake meta-toolchain`.

Typically set in the image recipe or in a *configuration file*.

If not set, no supplier information is added to the SDK SBOM.

See also *SPDX\_IMAGE\_SUPPLIER* and *SPDX\_PACKAGE\_SUPPLIER*.

### *SPDX\_UUID\_NAMESPACE*

The namespace used for generating UUIDs in SPDX documents. This should be a domain name or unique identifier for your organization to ensure globally unique SPDX IDs across different builds and organizations.

The default value is set to a domain managed by the OpenEmbedded project. You can override this to use your organization's domain.

### ***SPDXLICENSEMAP***

Maps commonly used license names to their SPDX counterparts found in `meta/files/common-licenses/`. For the default *SPDXLICENSEMAP* mappings, see the `meta/conf/licenses.conf` file.

For additional information, see the *LICENSE* variable.

### ***SPECIAL\_PKGSUFFIX***

A list of prefixes for *PN* used by the OpenEmbedded build system to create variants of recipes or packages. The list specifies the prefixes to strip off during certain circumstances such as the generation of the *BPN* variable.

### ***SPL\_BINARY***

The file type for the Secondary Program Loader (SPL). Some devices use an SPL from which to boot (e.g. the BeagleBone development board). For such cases, you can declare the file type of the SPL binary in the `u-boot.inc` include file, which is used in the U-Boot recipe.

The SPL file type is set to "null" by default in the `u-boot.inc` file as follows:

```
# Some versions of u-boot build an SPL (Second Program Loader) image that
# should be packaged along with the u-boot binary as well as placed in the
# deploy directory. For those versions they can set the following variables
# to allow packaging the SPL.

SPL_BINARY ?= ""

SPL_BINARYNAME ?= "${@os.path.basename(d.getVar("SPL_BINARY"))}"

SPL_IMAGE ?= "${SPL_BINARYNAME}-${MACHINE}-${PV}-${PR}"

SPL_SYMLINK ?= "${SPL_BINARYNAME}-${MACHINE}"
```

The *SPL\_BINARY* variable helps form various *SPL\_\** variables used by the OpenEmbedded build system.

See the BeagleBone machine configuration example in the "*Aggiungere un Layer Utilizzando lo Script bitbake-layers*" section in the Yocto Project Board Support Package Developer's Guide for additional information.

### ***SPL\_DTB\_BINARY***

When inheriting the *uboot-sign* class, the *SPL\_DTB\_BINARY* variable contains the name of the SPL binary to be compiled.

### ***SPL\_MKIMAGE\_DTCOPTS***

Options for the device tree compiler passed to `mkimage -D` feature while creating a FIT image with the *uboot-sign* class. If *SPL\_MKIMAGE\_DTCOPTS* is not set then the *uboot-sign* class will not pass the `-D` option to `mkimage`.

The default value is set to "" by the *uboot-config* class.

### ***SPL\_SIGN\_ENABLE***

Enable signing of the U-Boot FIT image. The default value is "0". This variable is used by the *uboot-sign* class.

### ***SPL\_SIGN\_KEYDIR***

Location of the directory containing the RSA key and certificate used for signing the U-Boot FIT image, used by the *uboot-sign* class.

### *SPL\_SIGN\_KEYNAME*

The name of keys used by the *uboot-sign* class for signing U-Boot FIT image stored in the *SPL\_SIGN\_KEYDIR* directory. If we have for example a *dev.key* key and a *dev.crt* certificate stored in the *SPL\_SIGN\_KEYDIR* directory, you will have to set *SPL\_SIGN\_KEYNAME* to *dev*.

### *SPLASH*

This variable, used by the *image* class, allows to choose splashscreen applications. Set it to the names of packages for such applications to use. This variable is set by default to *psplash*.

### *SPLASH\_IMAGES*

This variable, used by the *psplash* recipe, allows to customize the default splashscreen image.

Specified images in PNG format are converted to *.h* files by the recipe, and are included in the *psplash* binary, so you won't find them in the root filesystem.

To make such a change, it is recommended to customize the *psplash* recipe in a custom layer. Here is an example structure for an ACME board:

```
meta-acme/recipes-core/psplash
├── files
│   └── logo-acme.png
└── psplash_%.bbappend
```

And here are the contents of the *psplash\_%.bbappend* file in this example:

```
SPLASH_IMAGES = "file://logo-acme.png;outsuffix=default"
FILESEXTRAPATHS:prepend := "${THISDIR}/files:"
```

You could even add specific configuration options for *psplash*, for example:

```
EXTRA_OECONF += "--disable-startup-msg --enable-img-fullscreen"
```

For information on append files, see the *"Appending Other Layers Metadata With Your Layer"* section.

### *SRC\_URI*

See the BitBake manual for the initial description for this variable: *SRC\_URI*.

The following features are added by OpenEmbedded and the Yocto Project.

There are standard and recipe-specific options. Here are standard ones:

- *apply* --- whether to apply the patch or not. The default action is to apply the patch.
- *striplevel* --- which striplevel to use when applying the patch. The default level is 1.
- *patchdir* --- specifies the directory in which the patch should be applied. The default is *\${S}*.

Here are options specific to recipes building code from a revision control system:

- *mindate* --- apply the patch only if *SRCDATE* is equal to or greater than *mindate*.
- *maxdate* --- apply the patch only if *SRCDATE* is not later than *maxdate*.
- *minrev* --- apply the patch only if *SRCREV* is equal to or greater than *minrev*.

- `maxrev` --- apply the patch only if `SRCREV` is not later than `maxrev`.
- `rev` --- apply the patch only if `SRCREV` is equal to `rev`.
- `notrev` --- apply the patch only if `SRCREV` is not equal to `rev`.

**i Nota**

If you want the build system to pick up files specified through a `SRC_URI` statement from your append file, you need to be sure to extend the `FILESPATH` variable by also using the `FILESEXTRAPATHS` variable from within your append file.

### `SRC_URI_OVERRIDES_PACKAGE_ARCH`

By default, the OpenEmbedded build system automatically detects whether `SRC_URI` contains files that are machine-specific. If so, the build system automatically changes `PACKAGE_ARCH`. Setting this variable to "0" disables this behavior.

### `SRCDATE`

The date of the source code used to build the package. This variable applies only if the source was fetched from a Source Code Manager (SCM).

### `SRCPV`

The variable `SRCPV` is deprecated. It was previously used to include source control information in `PV` for *bitbake* to work correctly but this is no longer a requirement. Source control information will be automatically included by *bitbake* in the variable `PKGVSRC` during packaging if the + sign is present in `PV`.

**i Nota**

The `SRCPV` variable used to be defined in the `meta/conf/bitbake.conf` configuration file in *OpenEmbedded-Core (OE-Core)* as follows:

```
SRCPV = "${@bb.fetch2.get_srcrev(d)}"
```

The `get_srcrev` function can still be used to include source control information in variables manually.

### `SRCREV`

The revision of the source code used to build the package. This variable applies to Subversion, Git, and Mercurial only. Note that if you want to build a fixed revision and you want to avoid performing a query on the remote repository every time BitBake parses your recipe, you should specify a `SRCREV` that is a full revision identifier (e.g. the full SHA hash in git) and not just a tag.



**Nota**

For information on limitations when inheriting the latest revision of software using *SRCREV*, see the *AUTO-REV* variable description and the "*Automatically Incrementing a Package Version Number*" section, which is in the Yocto Project Development Tasks Manual.

***SRCREV\_FORMAT***

See *SRCREV\_FORMAT* in the BitBake manual.

***SRCTREECOVEREDTASKS***

A list of tasks that are typically not relevant (and therefore skipped) when building using the *externalsrc* class. The default value as set in that class file is the set of tasks that are rarely needed when using external source:

```
SRCTREECOVEREDTASKS ?= "do_patch do_unpack do_fetch"
```

The notable exception is when processing external kernel source as defined in the *kernel-yocto* class file (formatted for aesthetics):

```
SRCTREECOVEREDTASKS += "\
do_validate_branches \
do_kernel_configcheck \
do_kernel_checkout \
do_fetch \
do_unpack \
do_patch \
"
```

See the associated *EXTERNALSRC* and *EXTERNALSRC\_BUILD* variables for more information.

***SSTATE\_DIR***

The directory for the shared state cache.

***SSTATE\_EXCLUDEDEPS\_SYSROOT***

This variable allows to specify indirect dependencies to exclude from sysroots, for example to avoid the situations when a dependency on any *-native* recipe will pull in all dependencies of that recipe in the recipe sysroot. This behaviour might not always be wanted, for example when that *-native* recipe depends on build tools that are not relevant for the current recipe.

This way, irrelevant dependencies are ignored, which could have prevented the reuse of prebuilt artifacts stored in the Shared State Cache.

*SSTATE\_EXCLUDEDEPS\_SYSROOT* is evaluated as two regular expressions of recipe and dependency to ignore. An example is the rule in *meta/conf/layer.conf*:

```
# Nothing needs to depend on libc-initial
# base-passwd/shadow-sysroot don't need their dependencies
SSTATE_EXCLUDEDEPS_SYSROOT += "\
.*->.*-initial.* \
```

(continues on next page)

(continua dalla pagina precedente)

```
.*(base-passwd|shadow-sysroot)->.* \
"
```

The `->` substring represents the dependency between the two regular expressions.

### ***SSTATE\_MIRROR\_ALLOW\_NETWORK***

If set to "1", allows fetches from mirrors that are specified in *SSTATE\_MIRRORS* to work even when fetching from the network is disabled by setting *BB\_NO\_NETWORK* to "1". Using the *SSTATE\_MIRROR\_ALLOW\_NETWORK* variable is useful if you have set *SSTATE\_MIRRORS* to point to an internal server for your shared state cache, but you want to disable any other fetching from the network.

### ***SSTATE\_MIRRORS***

Configures the OpenEmbedded build system to search other mirror locations for prebuilt cache data objects before building out the data. This variable works like fetcher *MIRRORS* and *PREMIRRORS* and points to the cache locations to check for the shared state (sstate) objects.

You can specify a filesystem directory or a remote URL such as HTTP or FTP. The locations you specify need to contain the shared state cache (sstate-cache) results from previous builds. The sstate-cache you point to can also be from builds on other machines.

The Yocto Project actually shares the cache data objects built by its autobuilder:

```
SSTATE_MIRRORS ?= "file://.* http://sstate.yoctoproject.org/all/PATH;
↪downloadfilename=PATH"
```

As such binary artifacts are built for the generic QEMU machines supported by the various Poky releases, they are less likely to be reusable in real projects building binaries optimized for a specific CPU family.

See the *Setting up a Shared State Cache Mirror* section of the Yocto Project Development Tasks Manual for details on how to setup a shared state mirror.

### ***SSTATE\_SCAN\_FILES***

Controls the list of files the OpenEmbedded build system scans for hardcoded installation paths. The variable uses a space-separated list of filenames (not paths) with standard wildcard characters allowed.

During a build, the OpenEmbedded build system creates a shared state (sstate) object during the first stage of preparing the sysroots. That object is scanned for hardcoded paths for original installation locations. The list of files that are scanned for paths is controlled by the *SSTATE\_SCAN\_FILES* variable. Typically, recipes add files they want to be scanned to the value of *SSTATE\_SCAN\_FILES* rather than the variable being comprehensively set. The *sstate* class specifies the default list of files.

For details on the process, see the *staging* class.

### ***SSTATE\_SIG\_KEY***

When signing *shared state* artifacts (when *SSTATE\_VERIFY\_SIG* is set to "1"), the *SSTATE\_SIG\_KEY* variable is the GPG key identifier used to sign them.

See *Firma dello Stato Condiviso* in the Yocto Project Security Manual for more information.

### *SSTATE\_SIG\_PASSPHRASE*

When signing *shared state* artifacts (when *SSTATE\_VERIFY\_SIG* is set to "1"), the *SSTATE\_SIG\_PASSPHRASE* variable is the passphrase used to protect the private key signing the artifacts.

See *Firma dello Stato Condiviso* in the Yocto Project Security Manual for more information.

### *SSTATE\_SKIP\_CREATION*

The *SSTATE\_SKIP\_CREATION* variable can be used to skip the creation of *shared state* tarball files. It makes sense e.g. for image creation tasks as tarring images and keeping them in sstate would consume a lot of disk space.

In general it is not recommended to use this variable as missing sstate artefacts adversely impact the build, particularly for entries in the middle of dependency chains. The case it can make sense is where the size and time costs of the artefact are similar to just running the tasks. This generally only applies to end artefact output like images.

The syntax to disable it for one task is:

```
SSTATE_SKIP_CREATION:task-image-complete = "1"
```

The syntax to disable it for the whole recipe is:

```
SSTATE_SKIP_CREATION = "1"
```

### *SSTATE\_VALID\_SIGS*

When verifying *shared state* artifacts (when *SSTATE\_VERIFY\_SIG* is set to "1"), the *SSTATE\_VALID\_SIGS* variable is a space-separated list of GPG key identifiers to use to verify their signature.

It must contain the short form identifier of the key pair. For example, when running the `gpg --list-keys` command (in bold text below):

```
pub   ed25519 2026-04-17 [SC]
       4049A47E3AAA99D0250966DC5B97632FA7F4E942
uid           [ultimate] Antonin Godard (SState Signing) <antonin.
→godard@bootlin.com>
sub    cv25519 2026-04-17 [E]
```

The short form equals the last 16 characters of the identifier. In the above example: 5B97632FA7F4E942.

#### Nota

If this variable is empty (the default), any of the GPG key present on the *Build Host* can be used by the *OpenEmbedded Build System* to verify the shared state artifacts.

See *Firma dello Stato Condiviso* in the Yocto Project Security Manual for more information.

### *SSTATE\_VERIFY\_SIG*

The *SSTATE\_VERIFY\_SIG* variable controls whether to enable or disable the *shared state* artifacts signing feature.

See *Firma dello Stato Condiviso* in the Yocto Project Security Manual for more information.

### ***STABLE\_VERSION\_PARTS***

The number of leading dot-separated components of *PV* that constitute the stable version prefix. Used by the *upstream-stable-release-point* class to generate *UPSTREAM\_STABLE\_RELEASE\_REGEX*. Defaults to "2".

For example, with *PV* = "259.5" and *STABLE\_VERSION\_PARTS* = "1", the generated regex matches versions starting with 259.

### ***STAGING\_BASE\_LIBDIR\_NATIVE***

Specifies the path to the */lib* subdirectory of the sysroot directory for the build host.

### ***STAGING\_BASELIBDIR***

Specifies the path to the */lib* subdirectory of the sysroot directory for the target for which the current recipe is being built (*STAGING\_DIR\_HOST*).

### ***STAGING\_BINDIR***

Specifies the path to the */usr/bin* subdirectory of the sysroot directory for the target for which the current recipe is being built (*STAGING\_DIR\_HOST*).

### ***STAGING\_BINDIR\_CROSS***

Specifies the path to the directory containing binary configuration scripts. These scripts provide configuration information for other software that wants to make use of libraries or include files provided by the software associated with the script.

#### ***i* Nota**

This style of build configuration has been largely replaced by *pkg-config*. Consequently, if *pkg-config* is supported by the library to which you are linking, it is recommended you use *pkg-config* instead of a provided configuration script.

### ***STAGING\_BINDIR\_NATIVE***

Specifies the path to the */usr/bin* subdirectory of the sysroot directory for the build host.

### ***STAGING\_DATADIR***

Specifies the path to the */usr/share* subdirectory of the sysroot directory for the target for which the current recipe is being built (*STAGING\_DIR\_HOST*).

### ***STAGING\_DATADIR\_NATIVE***

Specifies the path to the */usr/share* subdirectory of the sysroot directory for the build host.

### ***STAGING\_DIR***

Used for constructing directory trees used during staging.

For information on how staging for recipe-specific sysroots occurs, see the *do\_populate\_sysroot* task, the "Sharing Files Between Recipes" section in the Yocto Project Development Tasks Manual, the "Configurazione, Compilazione e Staging" section in the Yocto Project Overview and Concepts Manual, and the *SYSROOT\_DIRS* variable.

**i Nota**

Recipes should never write files directly under the *STAGING\_DIR* directory because the OpenEmbedded build system manages the directory automatically. Instead, files should be installed to  $\{D\}$  within your recipe's *do\_install* task and then the OpenEmbedded build system will stage a subset of those files into the sysroot.

***STAGING\_DIR\_HOST***

Specifies the path to the recipe's input sysroot directory, populated with files for the system on which the component is built to run (the system that hosts the component). For most recipes, this sysroot is populated by their *do\_populate\_sysroot* task (when sharing files between recipes). Exceptions include native recipes, for which the files from *do\_populate\_sysroot* task are instead copied to *STAGING\_DIR\_NATIVE*. Depending on the type of recipe and the build target, *STAGING\_DIR\_HOST* can have the following values:

- For recipes building for the target machine, the value is " $\{RECIPE\_SYSROOT\}$ ", check *RECIPE\_SYSROOT*.
- For native recipes (building for the *build host*), the value is empty given the assumption that when building for the *build host*, the *build host*'s own directories should be used.

**i Nota**

Native recipe files are not installed into host paths such as `/usr`. Rather, such files are installed into *STAGING\_DIR\_NATIVE*. When compiling native recipes, standard build environment variables such as *CPPFLAGS* and *CFLAGS* are set up so that both *build host*'s paths and *STAGING\_DIR\_NATIVE* are searched for libraries and headers using, for example, GCC's `-isystem` option.

Thus, the emphasis is that the *STAGING\_DIR\** variables should be viewed as input variables by tasks such as *do\_configure*, *do\_compile*, and *do\_install*. Having the real system root (the *build host*'s root) play the role of *STAGING\_DIR\_HOST* makes conceptual sense for native recipes, as they make use of the *build host*'s headers and libraries.

***STAGING\_DIR\_NATIVE***

Specifies the path to the recipe's input sysroot directory, populated with files provided by native recipes (recipes building components that run on the *build host* itself).

The default value is " $\{RECIPE\_SYSROOT\_NATIVE\}$ ", check *RECIPE\_SYSROOT\_NATIVE*.

***STAGING\_DIR\_TARGET***

Specifies the path to the sysroot used for the system for which the component generates code. For components that do not generate code, which is the majority, *STAGING\_DIR\_TARGET* is set to match *STAGING\_DIR\_HOST*.

Some recipes build binaries that can run on the target system but those binaries in turn generate code for another different system (e.g. *cross-canadian* recipes). Using terminology from GNU, the primary system is referred to as the "HOST" and the secondary, or different, system is referred to as the "TARGET". Thus, the binaries run on the "HOST" system and generate binaries for the "TARGET" system. The *STAGING\_DIR\_HOST* variable

points to the sysroot used for the "HOST" system, while *STAGING\_DIR\_TARGET* points to the sysroot used for the "TARGET" system.

#### *STAGING\_ETCDIR\_NATIVE*

Specifies the path to the `/etc` subdirectory of the sysroot directory for the build host.

#### *STAGING\_EXECPREFIXDIR*

Specifies the path to the `/usr` subdirectory of the sysroot directory for the target for which the current recipe is being built (*STAGING\_DIR\_HOST*).

#### *STAGING\_INCDIR*

Specifies the path to the `/usr/include` subdirectory of the sysroot directory for the target for which the current recipe being built (*STAGING\_DIR\_HOST*).

#### *STAGING\_INCDIR\_NATIVE*

Specifies the path to the `/usr/include` subdirectory of the sysroot directory for the build host.

#### *STAGING\_KERNEL\_BUILDDIR*

Points to the directory containing the kernel build artifacts. Recipes building software that needs to access kernel build artifacts (e.g. `systemtap-uprobes`) can look in the directory specified with the *STAGING\_KERNEL\_BUILDDIR* variable to find these artifacts after the kernel has been built.

#### *STAGING\_KERNEL\_DIR*

The directory with kernel headers that are required to build out-of-tree modules.

#### *STAGING\_LIBDIR*

Specifies the path to the `/usr/lib` subdirectory of the sysroot directory for the target for which the current recipe is being built (*STAGING\_DIR\_HOST*).

#### *STAGING\_LIBDIR\_NATIVE*

Specifies the path to the `/usr/lib` subdirectory of the sysroot directory for the build host.

#### *STAMP*

Specifies the base path used to create recipe stamp files. The path to an actual stamp file is constructed by evaluating this string and then appending additional information. Currently, the default assignment for *STAMP* as set in the `meta/conf/bitbake.conf` file is:

```
STAMP = "${STAMPS_DIR}/${MULTIMACH_TARGET_SYS}/${PN}/${EXTENDPE}${PV}-${PR}"
```

Per informazioni su come BitBake utilizza i file di timestamp per determinare se un task deve essere rieseguito, consultare la sezione "*File Stamp e Riesecuzione dei Task*" nel Manuale Introduttivo e Concetti di Yocto Project.

See *STAMPS\_DIR*, *MULTIMACH\_TARGET\_SYS*, *PN*, *EXTENDPE*, *PV*, and *PR* for related variable information.

#### *STAMPCLEAN*

See *STAMPCLEAN* in the BitBake manual.

#### *STAMPS\_DIR*

Specifies the base directory in which the OpenEmbedded build system places stamps. The default directory is `${TMPDIR}/stamps`.

### STRIP

The minimal command and arguments to run `strip`, which is used to strip symbols.

### SUMMARY

The short (72 characters or less) summary of the binary package for packaging systems such as `opkg`, `rpm`, or `dpkg`. By default, `SUMMARY` is used to define the `DESCRIPTION` variable if `DESCRIPTION` is not set in the recipe.

If you don't set this variable in your recipe file, you will be warned about that and it will be set to a default value from the `meta/conf/bitbake.conf` file.

### SVNDIR

The directory in which files checked out of a Subversion system are stored.

### SYSLINUX\_DEFAULT\_CONSOLE

Specifies the kernel boot default console. If you want to use a console other than the default, set this variable in your recipe as follows where "X" is the console number you want to use:

```
SYSLINUX_DEFAULT_CONSOLE = "console=ttyX"
```

The `syslinux` class initially sets this variable to null but then checks for a value later.

### SYSLINUX\_OPTS

Lists additional options to add to the `syslinux` file. You need to set this variable in your recipe. If you want to list multiple options, separate the options with a semicolon character (;).

The `syslinux` class uses this variable to create a set of options.

### SYSLINUX\_SERIAL

Specifies the alternate serial port or turns it off. To turn off serial, set this variable to an empty string in your recipe. The variable's default value is set in the `syslinux` class as follows:

```
SYSLINUX_SERIAL ?= "0 115200"
```

The class checks for and uses the variable as needed.

### SYSLINUX\_SERIAL\_TTY

Specifies the alternate console=tty... kernel boot argument. The variable's default value is set in the `syslinux` class as follows:

```
SYSLINUX_SERIAL_TTY ?= "console=ttyS0,115200"
```

The class checks for and uses the variable as needed.

### SYSLINUX\_SPLASH

An `.LSS` file used as the background for the VGA boot menu when you use the boot menu. You need to set this variable in your recipe.

The `syslinux` class checks for this variable and if found, the OpenEmbedded build system installs the splash screen.

### *SYSROOT\_DESTDIR*

Points to the temporary directory under the work directory (default "`${WORKDIR}/sysroot-destdir`") where the files populated into the sysroot are assembled during the *do\_populate\_sysroot* task.

### *SYSROOT\_DIRS*

Directories that are staged into the sysroot by the *do\_populate\_sysroot* task. By default, the following directories are staged:

```
SYSROOT_DIRS = " \
    ${includedir} \
    ${libdir} \
    ${base_libdir} \
    ${nonarch_base_libdir} \
    ${datadir} \
    /sysroot-only \
"
```

Consider the following example in which you need to manipulate this variable. Assume you have a recipe A that provides a shared library `.so.*` that is installed into a custom folder other than "`${libdir}`" or "`${base_libdir}`", let's say "`/opt/lib`".

#### **i** Nota

This is not a recommended way to deal with shared libraries, but this is just to show the usefulness of setting *SYSROOT\_DIRS*.

When a recipe B *DEPENDS* on A, it means what is in *SYSROOT\_DIRS* will be copied from *D* of the recipe A into B's *SYSROOT\_DESTDIR* that is "`${WORKDIR}/sysroot-destdir`".

Now, since `/opt/lib` is not in *SYSROOT\_DIRS*, it will never be copied to A's *RECIPE\_SYSROOT*, which is "`${WORKDIR}/recipe-sysroot`". So, the linking process will fail.

To fix this, you need to add `/opt/lib` to *SYSROOT\_DIRS*:

```
SYSROOT_DIRS:append = " /opt/lib"
```

#### **i** Nota

Even after setting `/opt/lib` to *SYSROOT\_DIRS*, the linking process will still fail because the linker does not know that location, since *TARGET\_LDFLAGS* doesn't contain it (if your recipe is for the target). Therefore, so you should add:

```
TARGET_LDFLAGS:append = " -L${RECIPE_SYSROOT}/opt/lib"
```

### *SYSROOT\_DIRS\_IGNORE*

Directories that are not staged into the sysroot by the *do\_populate\_sysroot* task. You can use this variable to



exclude certain subdirectories of directories listed in *SYSROOT\_DIRS* from staging. By default, the following directories are not staged:

```
SYSROOT_DIRS_IGNORE = " \  
    ${mandir} \  
    ${docdir} \  
    ${infodir} \  
    ${datadir}/X11/locale \  
    ${datadir}/applications \  
    ${datadir}/bash-completion \  
    ${datadir}/fonts \  
    ${datadir}/gtk-doc/html \  
    ${datadir}/installed-tests \  
    ${datadir}/locale \  
    ${datadir}/pixmapes \  
    ${datadir}/terminfo \  
    ${libdir}/${BPN}/ptest \  
"
```

### *SYSROOT\_DIRS\_NATIVE*

Extra directories staged into the sysroot by the *do\_populate\_sysroot* task for *-native* recipes, in addition to those specified in *SYSROOT\_DIRS*. By default, the following extra directories are staged:

```
SYSROOT_DIRS_NATIVE = " \  
    ${bindir} \  
    ${sbindir} \  
    ${base_bindir} \  
    ${base_sbindir} \  
    ${libexecdir} \  
    ${sysconfdir} \  
    ${localstatedir} \  
"
```

**i Nota**

Programs built by `-native` recipes run directly from the sysroot (*STAGING\_DIR\_NATIVE*), which is why additional directories containing program executables and supporting files need to be staged.

***SYSROOT\_PREPROCESS\_FUNCS***

A list of functions to execute after files are staged into the sysroot. These functions are usually used to apply additional processing on the staged files, or to stage additional files.

***SYSTEMD\_AUTO\_ENABLE***

When inheriting the *systemd* class, this variable specifies whether the specified service in *SYSTEMD\_SERVICE* should start automatically or not. By default, the service is enabled to automatically start at boot time. The default setting is in the *systemd* class as follows:

```
SYSTEMD_AUTO_ENABLE ??= "enable"
```

You can disable the service by setting the variable to "disable".

***SYSTEMD\_BOOT\_CFG***

When *EFI\_PROVIDER* is set to "systemd-boot", the *SYSTEMD\_BOOT\_CFG* variable specifies the configuration file that should be used. By default, the *systemd-boot* class sets the *SYSTEMD\_BOOT\_CFG* as follows:

```
SYSTEMD_BOOT_CFG ?= "${S}/loader.conf"
```

For information on Systemd-boot, see the [Systemd-boot documentation](#).

***SYSTEMD\_BOOT\_ENTRIES***

When *EFI\_PROVIDER* is set to "systemd-boot", the *SYSTEMD\_BOOT\_ENTRIES* variable specifies a list of entry files (\*.conf) to install that contain one boot entry per file. By default, the *systemd-boot* class sets the *SYSTEMD\_BOOT\_ENTRIES* as follows:

```
SYSTEMD_BOOT_ENTRIES ?= ""
```

For information on Systemd-boot, see the [Systemd-boot documentation](#).

***SYSTEMD\_BOOT\_TIMEOUT***

When *EFI\_PROVIDER* is set to "systemd-boot", the *SYSTEMD\_BOOT\_TIMEOUT* variable specifies the boot menu timeout in seconds. By default, the *systemd-boot* class sets the *SYSTEMD\_BOOT\_TIMEOUT* as follows:

```
SYSTEMD_BOOT_TIMEOUT ?= "10"
```

For information on Systemd-boot, see the [Systemd-boot documentation](#).

***SYSTEMD\_DEFAULT\_TARGET***

This variable allows to set the default unit that systemd starts at bootup. Usually, this is either `multi-user.target` or `graphical.target`. This works by creating a `default.target` symbolic link to the chosen systemd target file.

See [systemd's documentation](#) for details.

For example, this variable is used in the `core-image-minimal-xfce.bb` recipe:

```
SYSTEMD_DEFAULT_TARGET = "graphical.target"
```

### SYSTEMD\_PACKAGES

When inheriting the `systemd` class, this variable locates the systemd unit files when they are not found in the main recipe's package. By default, the `SYSTEMD_PACKAGES` variable is set such that the systemd unit files are assumed to reside in the recipe's main package:

```
SYSTEMD_PACKAGES ?= "${PN}"
```

If these unit files are not in this recipe's main package, you need to use `SYSTEMD_PACKAGES` to list the package or packages in which the build system can find the systemd unit files.

### SYSTEMD\_SERVICE

When inheriting the `systemd` class, this variable specifies the systemd service name for a package.

Multiple services can be specified, each one separated by a space.

When you specify this file in your recipe, use a package name override to indicate the package to which the value applies. Here is an example from the `connman` recipe:

```
SYSTEMD_SERVICE:${PN} = "connman.service"
```

The package overrides that can be specified are directly related to the value of `SYSTEMD_PACKAGES`. Overrides not included in `SYSTEMD_PACKAGES` will be silently ignored.

### SYSVINIT\_ENABLED\_GETTYS

When using `SysVinit`, specifies a space-separated list of the virtual terminals that should run a `getty` (allowing login), assuming `USE_VT` is not set to "0".

The default value for `SYSVINIT_ENABLED_GETTYS` is "1" (i.e. only run a `getty` on the first virtual terminal).

### T

This variable points to a directory where BitBake places temporary files, which consist mostly of task logs and scripts, when building a particular recipe. The variable is typically set as follows:

```
T = "${WORKDIR}/temp"
```

The `WORKDIR` is the directory into which BitBake unpacks and builds the recipe. The default `bitbake.conf` file sets this variable.

The `T` variable is not to be confused with the `TMPDIR` variable, which points to the root of the directory tree where BitBake places the output of an entire build.

### TARGET\_ARCH

The target machine's architecture. The OpenEmbedded build system supports many architectures. Here is an example list of architectures supported. This list is by no means complete as the architecture is configurable:

- arm
- i586

- x86\_64
- powerpc
- powerpc64
- mips
- mipsel

For additional information on machine architectures, see the *TUNE\_ARCH* variable.

### ***TARGET\_AS\_ARCH***

Specifies architecture-specific assembler flags for the target system. *TARGET\_AS\_ARCH* is initialized from *TUNE\_ASARGS* by default in the BitBake configuration file (`meta/conf/bitbake.conf`):

```
TARGET_AS_ARCH = "${TUNE_ASARGS}"
```

### ***TARGET\_CC\_ARCH***

Specifies architecture-specific C compiler flags for the target system. *TARGET\_CC\_ARCH* is initialized from *TUNE\_CCARGS* by default.

#### **i Nota**

It is a common workaround to append *LDFLAGS* to *TARGET\_CC\_ARCH* in recipes that build software for the target that would not otherwise respect the exported *LDFLAGS* variable.

### ***TARGET\_CC\_KERNEL\_ARCH***

This is a specific kernel compiler flag for a CPU or Application Binary Interface (ABI) tune. The flag is used rarely and only for cases where a userspace *TUNE\_CCARGS* is not compatible with the kernel compilation. The *TARGET\_CC\_KERNEL\_ARCH* variable allows the kernel (and associated modules) to use a different configuration. See the `meta/conf/machine/include/arm/feature-arm-thumb.inc` file in *OpenEmbedded-Core (OE-Core)* for an example.

### ***TARGET\_CFLAGS***

Specifies the flags to pass to the C compiler when building for the target. When building in the target context, *CFLAGS* is set to the value of this variable by default.

Additionally, the SDK's environment setup script sets the *CFLAGS* variable in the environment to the *TARGET\_CFLAGS* value so that executables built using the SDK also have the flags applied.

### ***TARGET\_CPPFLAGS***

Specifies the flags to pass to the C pre-processor (i.e. to both the C and the C++ compilers) when building for the target. When building in the target context, *CPPFLAGS* is set to the value of this variable by default.

Additionally, the SDK's environment setup script sets the *CPPFLAGS* variable in the environment to the *TARGET\_CPPFLAGS* value so that executables built using the SDK also have the flags applied.

### ***TARGET\_CXXFLAGS***

Specifies the flags to pass to the C++ compiler when building for the target. When building in the target context, *CXXFLAGS* is set to the value of this variable by default.

Additionally, the SDK's environment setup script sets the `CXXFLAGS` variable in the environment to the `TARGET_CXXFLAGS` value so that executables built using the SDK also have the flags applied.

### `TARGET_DBGSRC_DIR`

Specifies the target path to debug source files. The default is `/usr/src/debug/${PN}/${PV}`.

### `TARGET_FPU`

Specifies the method for handling FPU code. For FPU-less targets, which include most ARM CPUs, the variable must be set to "soft". If not, the kernel emulation gets used, which results in a performance penalty.

### `TARGET_LD_ARCH`

Specifies architecture-specific linker flags for the target system. `TARGET_LD_ARCH` is initialized from `TUNE_LDARGS` by default in the BitBake configuration file (`meta/conf/bitbake.conf`):

```
TARGET_LD_ARCH = "${TUNE_LDARGS}"
```

### `TARGET_LDFLAGS`

Specifies the flags to pass to the linker when building for the target. When building in the target context, `LD_FLAGS` is set to the value of this variable by default.

Additionally, the SDK's environment setup script sets the `LD_FLAGS` variable in the environment to the `TARGET_LDFLAGS` value so that executables built using the SDK also have the flags applied.

### `TARGET_OS`

Specifies the target's operating system. The variable can be set to "linux" for glibc-based systems (GNU C Library) and to "linux-musl" for musl libc. For ARM/EABI targets, the possible values are "linux-gnueabi" and "linux-musleabi".

### `TARGET_PREFIX`

Specifies the prefix used for the toolchain binary target tools.

Depending on the type of recipe and the build target, `TARGET_PREFIX` is set as follows:

- For recipes building for the target machine, the value is `"${TARGET_SYS}"`.
- For native recipes, the build system sets the variable to the value of `BUILD_PREFIX`.
- For native SDK recipes (*nativesdk*), the build system sets the variable to the value of `SDK_PREFIX`.

### `TARGET_SYS`

Specifies the system, including the architecture and the operating system, for which the build is occurring in the context of the current recipe.

The OpenEmbedded build system automatically sets this variable based on `TARGET_ARCH`, `TARGET_VENDOR`, and `TARGET_OS` variables.

#### Nota

You do not need to set the `TARGET_SYS` variable yourself.

Consider these two examples:

- Given a native recipe on a 32-bit, x86 machine running Linux, the value is "i686-linux".

- Given a recipe being built for a little-endian, MIPS target running Linux, the value might be "mipsel-linux".

### **TARGET\_VENDOR**

Specifies the name of the target vendor.

### **TC\_CXX\_RUNTIME**

Specifies the C/C++ STL and runtime variant to use during the build process. Default value is 'gnu'

You can select "gnu", "llvm", or "android".

### **TCLIBC**

Specifies the GNU standard C library (`libc`) variant to use during the build process.

You can select "glibc", "musl", "newlib", or "baremetal".

### **TCMODE**

Specifies the toolchain selector. *TCMODE* controls the characteristics of the generated packages and images by telling the OpenEmbedded build system which toolchain profile to use. By default, the OpenEmbedded build system builds its own internal toolchain. The variable's default value is "default", which uses that internal toolchain.

#### **Nota**

If *TCMODE* is set to a value other than "default", then it is your responsibility to ensure that the toolchain is compatible with the default toolchain. Using older or newer versions of these components might cause build problems. See [Release Information](#) for your version of the Yocto Project, to find the specific components with which the toolchain must be compatible.

The *TCMODE* variable is similar to *TCLIBC*, which controls the variant of the GNU standard C library (`libc`) used during the build process: `glibc` or `musl`.

With additional layers, it is possible to use a pre-compiled external toolchain. One example is the Sourcery G++ Toolchain. The support for this toolchain resides in the separate Mentor Graphics `meta-sourcery` layer at <https://github.com/MentorEmbedded/meta-sourcery/>.

The layer's `README` file contains information on how to use the Sourcery G++ Toolchain as an external toolchain. You will have to add the layer to your `build/conf/bblayers.conf` file and then set the *EXTERNAL\_TOOLCHAIN* variable in your `build/conf/local.conf` file to the location of the toolchain.

The fundamentals used for this example apply to any external toolchain. You can use `meta-sourcery` as a template for adding support for other external toolchains.

In addition to toolchain configuration, you will also need a corresponding toolchain recipe file. This recipe file needs to package up any pre-built objects in the toolchain such as `libgcc`, `libstdc++`, any locales, and `libc`.

### **TEMPLATECONF**

Specifies the directory used by the build system to find templates from which to build the `build/conf/bblayers.conf` and `build/conf/local.conf` files. Use this variable if you wish to customize such files, and the default BitBake targets shown when sourcing the `oe-init-build-env` script.

For details, see the *Creating a Custom Template Configuration Directory* section in the Yocto Project Development Tasks manual.

**Nota**

You must set this variable in the external environment in order for it to work.

***TEST\_EXPORT\_DIR***

The location the OpenEmbedded build system uses to export tests when the *TEST\_EXPORT\_ONLY* variable is set to "1".

The *TEST\_EXPORT\_DIR* variable defaults to "`${TMPDIR}/testimage/${PN}`".

***TEST\_EXPORT\_ONLY***

Specifies to export the tests only. Set this variable to "1" if you do not want to run the tests but you want them to be exported in a manner that you to run them outside of the build system.

***TEST\_LOG\_DIR***

Holds the SSH log and the boot log for QEMU machines. The *TEST\_LOG\_DIR* variable defaults to "`${WORKDIR}/testimage`".

**Nota**

Actual test results reside in the task log (`log.do_testimage`), which is in the `${WORKDIR}/temp/` directory.

***TEST\_POWERCONTROL\_CMD***

For automated hardware testing, specifies the command to use to control the power of the target machine under test. Typically, this command would point to a script that performs the appropriate action (e.g. interacting with a web-enabled power strip). The specified command should expect to receive as the last argument "off", "on" or "cycle" specifying to power off, on, or cycle (power off and then power on) the device, respectively.

***TEST\_POWERCONTROL\_EXTRA\_ARGS***

For automated hardware testing, specifies additional arguments to pass through to the command specified in *TEST\_POWERCONTROL\_CMD*. Setting *TEST\_POWERCONTROL\_EXTRA\_ARGS* is optional. You can use it if you wish, for example, to separate the machine-specific and non-machine-specific parts of the arguments.

***TEST\_QEMUBOOT\_TIMEOUT***

The time in seconds allowed for an image to boot before automated runtime tests begin to run against an image. The default timeout period to allow the boot process to reach the login prompt is 500 seconds. You can specify a different value in a *configuration file*.

For more information on testing images, see the "*Performing Automated Runtime Testing*" section in the Yocto Project Test Environment Manual.

***TEST\_SERIALCONTROL\_CMD***

For automated hardware testing, specifies the command to use to connect to the serial console of the target machine under test. This command simply needs to connect to the serial console and forward that connection to standard input and output as any normal terminal program does.

For example, to use the Picocom terminal program on serial device `/dev/ttyUSB0` at 115200bps, you would set the variable as follows:

```
TEST_SERIALCONTROL_CMD = "picocom /dev/ttyUSB0 -b 115200"
```

### ***TEST\_SERIALCONTROL\_CONNECT\_TIMEOUT***

For automated hardware testing with the *testexport* class, the *TEST\_SERIALCONTROL\_CONNECT\_TIMEOUT* variable specifies the timeout in seconds for the initial connection to the target.

### ***TEST\_SERIALCONTROL\_EXTRA\_ARGS***

For automated hardware testing, specifies additional arguments to pass through to the command specified in *TEST\_SERIALCONTROL\_CMD*. Setting *TEST\_SERIALCONTROL\_EXTRA\_ARGS* is optional. You can use it if you wish, for example, to separate the machine-specific and non-machine-specific parts of the command.

### ***TEST\_SERIALCONTROL\_PSI***

For automated hardware testing with the *testexport* class, the *TEST\_SERIALCONTROL\_PSI* variable specifies a regex string representing an empty prompt on the target terminal. For example: `root@target:.*#`.

### ***TEST\_SERVER\_IP***

The IP address of the build machine (host machine). This IP address is usually automatically detected. However, if detection fails, this variable needs to be set to the IP address of the build machine (i.e. where the build is taking place).

#### ***i* Nota**

The *TEST\_SERVER\_IP* variable is only used for a small number of tests such as the "dnf" test suite, which needs to download packages from `WORKDIR/oe-rootfs-repo`.

### ***TEST\_SUITES***

An ordered list of tests (modules) to run against an image when performing automated runtime testing.

The OpenEmbedded build system provides a core set of tests that can be used against images.

#### ***i* Nota**

Currently, there is only support for running these tests under QEMU.

Tests include `ping`, `ssh`, `df` among others. You can add your own tests to the list of tests by appending *TEST\_SUITES* as follows:

```
TEST_SUITES:append = " mytest"
```

Alternatively, you can provide the "auto" option to have all applicable tests run against the image:

```
TEST_SUITES:append = " auto"
```

Using this option causes the build system to automatically run tests that are applicable to the image. Tests that are not applicable are skipped.



The order in which tests are run is important. Tests that depend on another test must appear later in the list than the test on which they depend. For example, if you append the list of tests with two tests (`test_A` and `test_B`) where `test_B` is dependent on `test_A`, then you must order the tests as follows:

```
TEST_SUITES = "test_A test_B"
```

For more information on testing images, see the "*Performing Automated Runtime Testing*" section in the Yocto Project Test Environment Manual.

### TEST\_TARGET

Specifies the target controller to use when running tests against a test image. The default controller to use is "qemu":

```
TEST_TARGET = "qemu"
```

A target controller is a class that defines how an image gets deployed on a target and how a target is started. A layer can extend the controllers by adding a module in the layer's `/lib/oeqa/controllers` directory and by inheriting the `BaseTarget` class, which is an abstract class that cannot be used as a value of `TEST_TARGET`.

You can provide the following arguments with `TEST_TARGET`:

- `"qemu"`: Boots a QEMU image and runs the tests. See the "*Enabling Runtime Tests on QEMU*" section in the Yocto Project Test Environment Manual for more information.
- `"simpleremote"`: Runs the tests on target hardware that is already up and running. The hardware can be on the network or it can be a device running an image on QEMU. You must also set `TEST_TARGET_IP` when you use "simpleremote".

#### Nota

This argument is defined in `meta/lib/oeqa/controllers/simpleremote.py`.

For information on running tests on hardware, see the "*Enabling Runtime Tests on Hardware*" section in the Yocto Project Test Environment Manual.

### TEST\_TARGET\_IP

The IP address of your hardware under test. The `TEST_TARGET_IP` variable has no effect when `TEST_TARGET` is set to "qemu".

When you specify the IP address, you can also include a port. Here is an example:

```
TEST_TARGET_IP = "192.168.1.4:2201"
```

Specifying a port is useful when SSH is started on a non-standard port or in cases when your hardware under test is behind a firewall or network that is not directly accessible from your host and you need to do port address translation.

### TESTIMAGE\_AUTO

Automatically runs the series of automated tests for images when an image is successfully built. Setting `TESTIMAGE_AUTO` to "1" causes any image that successfully builds to automatically boot under QEMU. Using

the variable also adds in dependencies so that any SDK for which testing is requested is automatically built first.

These tests are written in Python making use of the `unittest` module, and the majority of them run commands on the target system over `ssh`. You can set this variable to "1" in a *configuration file* to have the OpenEmbedded build system automatically run these tests after an image successfully builds:

```
TESTIMAGE_AUTO = "1"
```

For more information on enabling, running, and writing these tests, see the "*Performing Automated Runtime Testing*" section in the Yocto Project Test Environment Manual and the "*testimage*" section.

### **TESTIMAGE\_FAILED\_QA\_ARTIFACTS**

When using the *testimage* class, the variable *TESTIMAGE\_FAILED\_QA\_ARTIFACTS* lists space-separated paths on the target to retrieve onto the host.

### **TESTSDK\_SUITES**

When using the *testsdk* class, the *TESTSDK\_SUITES* variable can be used to control the list of test modules to run. The default value for this variable is an empty string and all test modules that can be found are run.

### **THISDIR**

The directory in which the file BitBake is currently parsing is located. Do not manually set this variable.

### **TIME**

The time the build was started. Times appear using the hour, minute, and second (HMS) format (e.g. "140159" for one minute and fifty-nine seconds past 1400 hours).

### **TMPDIR**

This variable is the base directory the OpenEmbedded build system uses for all build output and intermediate files (other than the shared state cache). By default, the *TMPDIR* variable points to `tmp` within the *Build Directory*.

If you want to establish this directory in a location other than the default, you can set it to another value in your *build/conf/site.conf* configuration file:

```
TMPDIR = "/another/location"
```

An example use for this scenario is to set *TMPDIR* to a local disk, which does not use NFS, while having the *Build Directory* use NFS.

The filesystem used by *TMPDIR* must have standard filesystem semantics (i.e. mixed-case files are unique, POSIX file locking, and persistent inodes). Due to various issues with NFS and bugs in some implementations, NFS does not meet this minimum requirement. Consequently, *TMPDIR* cannot be on NFS.

### **TOOLCHAIN**

The *TOOLCHAIN* variable can be used to override the toolchain used by a recipe.

The default value for this variable is the value of *PREFERRED\_TOOLCHAIN*. See the description of *PREFERRED\_TOOLCHAIN* to know the list of possible values for *TOOLCHAIN*.

It is possible to override the value of this variable from a recipe if this recipe is known to support only a specific toolchain. For example, the *Pseudo* recipe overrides this variable to "gcc", because Pseudo uses GCC compiler built-ins options that the Clang/LLVM compiler does not provide.

### TOOLCHAIN\_HOST\_TASK

This variable lists packages the OpenEmbedded build system uses when building an SDK, which contains a cross-development environment. The packages specified by this variable are part of the toolchain set that runs on the *SDKMACHINE*, and each package should usually have the prefix `nativesdk-`. For example, consider the following command when building an SDK:

```
$ bitbake -c populate_sdk imagename
```

In this case, a default list of packages is set in this variable, but you can add additional packages to the list. See the "*Adding Individual Packages to the Standard SDK*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual for more information.

For background information on cross-development toolchains in the Yocto Project development environment, see the "*The Cross-Development Toolchain*" section in the Yocto Project Application Development and Software Development Kits (SDK/eSDK) Manual. For information on setting up a cross-development environment, see the *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)* manual.

Note that this variable applies to building an SDK, not an eSDK, in which case the *TOOLCHAIN\_HOST\_TASK\_ESDK* setting should be used instead.

### TOOLCHAIN\_HOST\_TASK\_ESDK

This variable allows to extend what is installed in the host portion of an eSDK. This is similar to *TOOLCHAIN\_HOST\_TASK* applying to SDKs.

### TOOLCHAIN\_NATIVE

The *TOOLCHAIN\_NATIVE* variable can be used to override the toolchain used by a *native* recipe.

The default value for this variable is the value of *PREFERRED\_TOOLCHAIN* (in *native* contexts). See the description of *PREFERRED\_TOOLCHAIN* to know the list of possible values for *TOOLCHAIN\_NATIVE*.

It is possible to override the value of this variable from a recipe if this recipe is known to support only a specific toolchain.

### TOOLCHAIN\_OPTIONS

This variable holds extra options passed to the compiler and the linker for non *-native* recipes as they have to point to their custom `sysroot` folder pointed to by *RECIPE\_SYSROOT*:

```
TOOLCHAIN_OPTIONS = " --sysroot=${RECIPE_SYSROOT}"
```

Native recipes don't need this variable to be set, as they are built for the host machine with the native compiler.

### TOOLCHAIN\_OUTPUTNAME

This variable defines the name used for the toolchain output. The *populate\_sdk\_base* class sets the *TOOLCHAIN\_OUTPUTNAME* variable as follows:

```
TOOLCHAIN_OUTPUTNAME ?= "${SDK_NAME}-toolchain-${SDK_VERSION}"
```

See the *SDK\_NAME* and *SDK\_VERSION* variables for additional information.

### TOOLCHAIN\_TARGET\_TASK

This variable lists packages the OpenEmbedded build system uses when it creates the target part of an SDK (i.e.

the part built for the target hardware), which includes libraries and headers. Use this variable to add individual packages to the part of the SDK that runs on the target. See the "[Adding Individual Packages to the Standard SDK](#)" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual for more information.

For background information on cross-development toolchains in the Yocto Project development environment, see the "[The Cross-Development Toolchain](#)" section in the Yocto Project Application Development and Software Development Kits (SDK/eSDK) Manual. For information on setting up a cross-development environment, see the *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)* manual.

### **TOPDIR**

See **TOPDIR** in the BitBake manual.

### **TRANSLATED\_TARGET\_ARCH**

A sanitized version of **TARGET\_ARCH**. This variable is used where the architecture is needed in a value where underscores are not allowed, for example within package filenames. In this case, dash characters replace any underscore characters used in **TARGET\_ARCH**.

Do not edit this variable.

### **TUNE\_ARCH**

The GNU canonical architecture for a specific architecture (i.e. arm, armeb, mips, mips64, and so forth). BitBake uses this value to setup configuration.

**TUNE\_ARCH** definitions are specific to a given architecture. The definitions can be a single static definition, or can be dynamically adjusted. You can see details for a given CPU family by looking at the architecture's README file. For example, the meta/conf/machine/include/mips/README file in *OpenEmbedded-Core (OE-Core)* provides information for **TUNE\_ARCH** specific to the mips architecture.

**TUNE\_ARCH** is tied closely to **TARGET\_ARCH**, which defines the target machine's architecture. The BitBake configuration file (meta/conf/bitbake.conf) sets **TARGET\_ARCH** as follows:

```
TARGET_ARCH = "${TUNE_ARCH}"
```

The following list, which is by no means complete since architectures are configurable, shows supported machine architectures:

- arm
- i586
- x86\_64
- powerpc
- powerpc64
- mips
- mipsel

### **TUNE\_ASARGS**

Specifies architecture-specific assembler flags for the target system. The set of flags is based on the se-

lected tune features. *TUNE\_ASARGS* is set using the tune include files, which are typically under `meta/conf/machine/include/` and are influenced through *TUNE\_FEATURES*. For example, the `meta/conf/machine/include/x86/arch-x86.inc` file defines the flags for the x86 architecture as follows:

```
TUNE_ASARGS += "${@bb.utils.contains("TUNE_FEATURES", "mx32", "-x32", "", d)}"
```

#### Nota

Board Support Packages (BSPs) select the tune. The selected tune, in turn, affects the tune variables themselves (i.e. the tune can supply its own set of flags).

### *TUNE\_CCARGS*

Specifies architecture-specific C compiler flags for the target system. The set of flags is based on the selected tune features. *TUNE\_CCARGS* is set using the tune include files, which are typically under `meta/conf/machine/include/` and are influenced through *TUNE\_FEATURES*.

#### Nota

Board Support Packages (BSPs) select the tune. The selected tune, in turn, affects the tune variables themselves (i.e. the tune can supply its own set of flags).

### *TUNE\_FEATURES*

Features used to "tune" a compiler for optimal use given a specific processor. The features are defined within the tune files and allow arguments (i.e. *TUNE\_\*ARGS*) to be dynamically generated based on the features.

The OpenEmbedded build system verifies the features to be sure they are not conflicting and that they are supported.

The BitBake configuration file (`meta/conf/bitbake.conf`) defines *TUNE\_FEATURES* as follows:

```
TUNE_FEATURES ??= "${TUNE_FEATURES:tune-${DEFAULTTUNE}}"
```

See the *DEFAULTTUNE* variable for more information.

### *TUNE\_LDARGS*

Specifies architecture-specific linker flags for the target system. The set of flags is based on the selected tune features. *TUNE\_LDARGS* is set using the tune include files, which are typically under `meta/conf/machine/include/` and are influenced through *TUNE\_FEATURES*. For example, the `meta/conf/machine/include/x86/arch-x86.inc` file defines the flags for the x86 architecture as follows:

```
TUNE_LDARGS += "${@bb.utils.contains("TUNE_FEATURES", "mx32", "-m elf32_x86_64
↪", "", d)}"
```

**Nota**

Board Support Packages (BSPs) select the tune. The selected tune, in turn, affects the tune variables themselves (i.e. the tune can supply its own set of flags).

**TUNE\_PKGARCH**

The package architecture understood by the packaging system to define the architecture, ABI, and tuning of output packages. The specific tune is defined using the `"_tune"` override as follows:

```
TUNE_PKGARCH:tune-tune = "tune"
```

These tune-specific package architectures are defined in the machine include files. Here is an example of the "core2-32" tuning as used in the `meta/conf/machine/include/x86/tune-core2.inc` file:

```
TUNE_PKGARCH:tune-core2-32 = "core2-32"
```

**TUNECONFLICTS**

Specifies CPU or Application Binary Interface (ABI) tuning features that conflict with feature.

Known tuning conflicts are specified in the machine include files in *OpenEmbedded-Core (OE-Core)*. Here is an example from the `meta/conf/machine/include/mips/arch-mips.inc` include file that lists the "o32" and "n64" features as conflicting with the "n32" feature:

```
TUNECONFLICTS[n32] = "o32 n64"
```

**TUNEVALID**

Specifies a valid CPU or Application Binary Interface (ABI) tuning feature. The specified feature is stored as a flag. Valid features are specified in the machine include files (e.g. `meta/conf/machine/include/arm/arch-arm.inc`). Here is an example from that file:

```
TUNEVALID[bigendian] = "Enable big-endian mode."
```

See the machine include files in *OpenEmbedded-Core (OE-Core)* for these features.

**UBOOT\_BINARY**

Specifies the name of the binary build by U-Boot.

**UBOOT\_CONFIG**

Configures one or more U-Boot configurations to build. Each configuration must define the `UBOOT_MACHINE` variable. Additional control variables are: `UBOOT_CONFIG_BINARY`, `UBOOT_CONFIG_FRAGMENTS`, `UBOOT_CONFIG_IMAGE_FSTYPES`, and `UBOOT_CONFIG_MAKE_OPTS`.

Here is an updated example from the `meta-freescale` layer.

```
UBOOT_CONFIG ??= "sdcard-ifc-secure-boot sdcard-ifc sdcard-qspi lpuart qspi_
↪secure-boot nor"

UBOOT_CONFIG[nor] = "ls1021atwr_nor_defconfig"
```

(continues on next page)

(continua dalla pagina precedente)

```

UBOOT_CONFIG[sdcard-ifc] = "ls1021atwr_sdcard_ifc_defconfig"
UBOOT_CONFIG[sdcard-qspi] = "ls1021atwr_sdcard_qspi_defconfig"
UBOOT_CONFIG[lpuart] = "ls1021atwr_nor_lpuart_defconfig"
UBOOT_CONFIG[qspi] = "ls1021atwr_qspi_defconfig"
UBOOT_CONFIG[secure-boot] = "ls1021atwr_nor_SECURE_BOOT_defconfig"
UBOOT_CONFIG[sdcard-ifc-secure-boot] = "ls1021atwr_sdcard_ifc_SECURE_BOOT_
→defconfig"

UBOOT_CONFIG_BINARY[sdcard-ifc] = "u-boot-with-spl-pbl.bin"
UBOOT_CONFIG_BINARY[sdcard-qspi] = "u-boot-with-spl-pbl.bin"
UBOOT_CONFIG_BINARY[sdcard-ifc-secure-boot] = "u-boot-with-spl-pbl.bin"

```

In this example, all possible seven configurations are selected. Each configuration specifies "...\_defconfig" as *UBOOT\_MACHINE*, and the "sd..." configurations define an individual name for *UBOOT\_CONFIG\_BINARY*.

For more information on how the *UBOOT\_CONFIG* variable is handled, see the *uboot-config* class.

### *UBOOT\_CONFIG\_BINARY*

This variable cannot be set to a value in a config, it is a placeholder for configuring the *UBOOT\_CONFIG* flow via flags:

```

UBOOT_CONFIG_BINARY[foo] = "binary1"
UBOOT_CONFIG_BINARY[bar] = "binary2"

```

It specifies the binary to select as the one to deploy in *DEPLOY\_DIR\_IMAGE*. The output of a U-Boot build may be more than one binary, for example:

```

u-boot.bin
u-boot-with-spl.bin

```

Setting the `binary` value to `u-boot-with-spl.bin` will make this binary the one deployed in *DEPLOY\_DIR\_IMAGE*. It is renamed to include the build configuration name in the process (`foo` or `bar` in the above example).

This option defaults to *UBOOT\_BINARY* if not specified.

For more information on how the *UBOOT\_CONFIG\_BINARY* variable is handled, see the *uboot-config* class.

### *UBOOT\_CONFIG\_FRAGMENTS*

This variable cannot be set to a value in a config, it is a placeholder for configuring the *UBOOT\_CONFIG* flow via flags:

```

UBOOT_CONFIG_FRAGMENTS[foo] = "frag1 frag2"
UBOOT_CONFIG_FRAGMENTS[bar] = "frag3"

```

It specifies a list of fragments from the source tree that should be combined with the defconfig from *UBOOT\_CONFIG* that are used during `do_configure()` to configure the build. These fragments are located in same `${S}/configs/` directory as the defconfig.

This option is not required and you only need to specify it for configs that need them.

For more information on how the `UBOOT_CONFIG_FRAGMENTS` variable is handled, see the `uboot-config` class.

### **`UBOOT_CONFIG_IMAGE_FSTYPES`**

This variable cannot be set to a value in a config, it is a placeholder for configuring the `UBOOT_CONFIG` flow via flags:

```
UBOOT_CONFIG_IMAGE_FSTYPES[foo] = "fstype1"
UBOOT_CONFIG_IMAGE_FSTYPES[bar] = "fstype2"
```

Append additional image types to the `IMAGE_FSTYPES` variable for image generation for this build configuration. This can allow building an extra image format that uses the binary generated by this build configuration.

This option is not required and you only need to specify flag settings for configs that need them.

For more information on how the `UBOOT_CONFIG_IMAGE_FSTYPES` variable is handled, see the `uboot-config` class.

### **`UBOOT_CONFIG_MAKE_OPTS`**

This variable cannot be set to a value in a config, it is a placeholder for configuring the `UBOOT_CONFIG` flow via flags:

```
UBOOT_CONFIG_MAKE_OPTS[foo] = "OPT1=foo OPT2=2"
UBOOT_CONFIG_MAKE_OPTS[bar] = "OPT1=bar"
```

It specifies a list of make command line options that are passed to the `make` command during `do_compile()`.

This option is not required and you only need to specify flag settings for configs that need them.

For more information on how the `UBOOT_CONFIG_MAKE_OPTS` is handled, see the `uboot-config` class.

### **`UBOOT_DTB_LOADADDRESS`**

Specifies the load address for the dtb image used by U-Boot. During FIT image creation, the `UBOOT_DTB_LOADADDRESS` variable is used in `kernel-fit-image` class to specify the load address to be used in creating the dtb sections of Image Tree Source for the FIT image.

### **`UBOOT_DTBO_LOADADDRESS`**

Specifies the load address for the dtbo image used by U-Boot. During FIT image creation, the `UBOOT_DTBO_LOADADDRESS` variable is used in `kernel-fit-image` class to specify the load address to be used in creating the dtbo sections of Image Tree Source for the FIT image.

### **`UBOOT_ENTRYPOINT`**

Specifies the entry point for the U-Boot image. During U-Boot image creation, the `UBOOT_ENTRYPOINT` variable is passed as a command-line parameter to the `uboot-mkimage` utility.

To pass a 64 bit address for FIT image creation, you will need to set: - The `FIT_ADDRESS_CELLS` variable for FIT image creation. - The `UBOOT_FIT_ADDRESS_CELLS` variable for U-Boot FIT image creation.

This variable is used by the `kernel-fit-image`, `kernel-uimage`, `kernel`, `uboot-config` and `uboot-sign` classes.



### UBOOT\_ENV

This variable allows to add additional environment variables or a script to be installed together with U-Boot. This file, typically `uEnv.txt` or `boot.cmd`, is installed in `/boot` as well as copied to the [DEPLOYDIR](#) directory.

For machine configurations needing one of these files a `.bbappend` file should include it in the [SRC\\_URI](#) of the U-Boot recipe.

If the variable [UBOOT\\_ENV\\_SUFFIX](#) is set to `scr` the script is packaged as a uImage (`mkimage -T script .`) otherwise it gets installed verbatim.

Some examples:

- Adding a script `boot.cmd` as a uImage to `/boot`:

```
UBOOT_ENV = "boot"
UBOOT_ENV_SUFFIX = "scr"
SRC_URI += "file://${UBOOT_ENV_SRC}"
```

- Adding a script `uEnv.txt` as a plain text file to `/boot`:

```
UBOOT_ENV = "uEnv"
UBOOT_ENV_SUFFIX = "txt"
SRC_URI += "file://${UBOOT_ENV_BINARY}"
```

### UBOOT\_ENV\_SRC\_SUFFIX

If [UBOOT\\_ENV\\_SUFFIX](#) is set to `scr` this is the suffix of the plain text script file as it is specified in the [SRC\\_URI](#) of the U-Boot recipe. It defaults to `cmd`.

### UBOOT\_ENV\_SUFFIX

If this variable is set to `scr` the script referred to by [UBOOT\\_ENV](#) gets packaged as a uImage before it gets installed. The default is `txt` which means the script is installed as-is, with no modification.

### UBOOT\_EXTLINUX

When inheriting the `uboot-extlinux-config` class in a U-Boot recipe, the [UBOOT\\_EXTLINUX](#) variable should be set to `"1"` to enable the class functionality (inheriting the class is not enough).

### UBOOT\_EXTLINUX\_CONF\_NAME

When inheriting the `uboot-extlinux-config` class, the [UBOOT\\_EXTLINUX\\_CONF\\_NAME](#) variable controls the name of the file used for booting, which is `extlinux.conf` by default.

### UBOOT\_EXTLINUX\_CONSOLE

When inheriting the `uboot-extlinux-config` class, the [UBOOT\\_EXTLINUX\\_CONSOLE](#) variable can be set to control the `console=` parameter of the Linux kernel command-line. For example:

```
UBOOT_EXTLINUX_CONSOLE = "console=ttyS0,115200n8"
```

This is added to the `APPEND` property of the `extlinux.conf` file used for booting.

### UBOOT\_EXTLINUX\_DEFAULT\_LABEL

When inheriting the `uboot-extlinux-config` class, the [UBOOT\\_EXTLINUX\\_DEFAULT\\_LABEL](#) variable can

be set to the name of the label to automatically boot after the timeout period (controlled with `UBOOT_EXTINUX_TIMEOUT`).

### ***UBOOT\_EXTINUX\_FDT***

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTINUX_FDT` variable can be set to control the FDT property of the `extlinux.conf` file used for booting, which controls the Linux kernel device tree to use. For example:

```
UBOOT_EXTINUX_FDT = "../am335x-bone.dtb"
```

#### ***i* Nota**

The above path is relative to the `extlinux.conf` file used for booting. It can also be absolute, with the path being the one as stored in the partition from which the `extlinux.conf` file is.

### ***UBOOT\_EXTINUX\_FDTDIR***

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTINUX_FDTDIR` variable can be set to control the FDTDIR property of the `extlinux.conf` file used for booting, which controls the directory where the Linux kernel device tree specified in the `fdtfile` U-Boot environment variable is. For example:

```
UBOOT_EXTINUX_FDTDIR = "../"
```

#### ***i* Nota**

The above path is relative to the `extlinux.conf` file used for booting. It can also be absolute, with the path being the one as stored in the partition from which the `extlinux.conf` file is.

### ***UBOOT\_EXTINUX\_FDTOVERLAYS***

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTINUX_FDT` variable can be set to control the FDTOVERLAYS property of the `extlinux.conf` file used for booting, which controls the Linux kernel device overlays tree to apply on top of the device tree. For example:

```
UBOOT_EXTINUX_FDTOVERLAYS = "../am335x-bone-wifi.dtbo"
```

#### ***i* Nota**

The above path is relative to the `extlinux.conf` file used for booting. It can also be absolute, with the path being the one as stored in the partition from which the `extlinux.conf` file is.

### ***UBOOT\_EXTINUX\_INITRD***

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTINUX_INITRD` variable is optional and sets the value of the INITRD property of the `extlinux.conf` file used for booting, if the `initramfs` is external to the Linux kernel (see `INITRAMFS_IMAGE_BUNDLE`). For example:

```
UBOOT_EXTLINUX_INITRD = "../ramdisk.tar.zst"
```

#### Nota

The above path is relative to the `extlinux.conf` file used for booting. It can also be absolute, with the path being the one as stored in the partition from which the `extlinux.conf` file is.

### *UBOOT\_EXTLINUX\_INSTALL\_DIR*

When inheriting the *uboot-extlinux-config* class, the *UBOOT\_EXTLINUX\_INSTALL\_DIR* variable controls the name of the directory where the `extlinux.conf` file used for booting is installed, relative to the root of the partition where the directory will belong.

### *UBOOT\_EXTLINUX\_KERNEL\_ARGS*

When inheriting the *uboot-extlinux-config* class, the *UBOOT\_EXTLINUX\_KERNEL\_ARGS* variable can be used to pass extra parameters to the Linux kernel command-line. For example:

```
UBOOT_EXTLINUX_KERNEL_ARGS = "rootwait ro"
```

This is included in the `APPEND` property of the `extlinux.conf` file used for booting.

### *UBOOT\_EXTLINUX\_KERNEL\_IMAGE*

When inheriting the *uboot-extlinux-config* class, the *UBOOT\_EXTLINUX\_KERNEL\_IMAGE* variable can be used to specify the `KERNEL` property of the `extlinux.conf` file used for booting, which controls the Linux kernel image to use. For example:

```
UBOOT_EXTLINUX_KERNEL_IMAGE = "../zImage"
```

#### Nota

The above path is relative to the `extlinux.conf` file used for booting. It can also be absolute, with the path being the one as stored in the partition from which the `extlinux.conf` file is.

#### Suggerimento

The *KERNEL\_IMAGETYPE* variable can be used to get the name of the current Linux kernel being built by its associated recipe.

### *UBOOT\_EXTLINUX\_LABELS*

When inheriting the *uboot-extlinux-config* class, the *UBOOT\_EXTLINUX\_LABELS* variable contains a list of labels (`LABEL` property of the `extlinux.conf` file used for booting) that can be used for booting. This list must contain at least one entry, and default to "linux".

When multiple labels are specified in this list, all of the *UBOOT\_EXTLINUX\_* variables should be specified with overrides-style assignments. For example, if the *UBOOT\_EXTLINUX\_LABELS* variable contains:

```
UBOOT_EXTLINUX_LABELS = "compressed uncompressed"
```

Then the `UBOOT_EXTLINUX_KERNEL_IMAGE` variable can be specified multiple times as follows:

```
UBOOT_EXTLINUX_KERNEL_IMAGE:compressed = "../zImage"
UBOOT_EXTLINUX_KERNEL_IMAGE:uncompressed = "../Image"
```

This will make the value of the `KERNEL` property be different in each of the associated labels.

Note that default values are used when no overrides-style assignments are found for the current label. For example, taking the above example again, the following assignment would apply to both `compressed` and `uncompressed` labels if and only if `UBOOT_EXTLINUX_FDT:compressed` and `UBOOT_EXTLINUX_FDT:uncompressed` aren't set:

```
UBOOT_EXTLINUX_FDT = "../am335x-bone-wifi.dtbo"
```

### `UBOOT_EXTLINUX_MENU_DESCRIPTION`

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTLINUX_MENU_DESCRIPTION` variable sets the value of the `LABEL` property of the `extlinux.conf` file. If not specified, the name of the label itself is used as the description.

### `UBOOT_EXTLINUX_MENU_TITLE`

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTLINUX_MENU_TITLE` variable sets the `MENU TITLE` property of the `extlinux.conf` file used for booting. This variable doesn't support the overrides-style syntax described in the definition of `UBOOT_EXTLINUX_LABELS` as it applies to the whole `extlinux.conf` file.

### `UBOOT_EXTLINUX_ROOT`

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTLINUX_ROOT` variable is mandatory and contains the `root=` parameter of the `Linux kernel command-line`. For example, the following would set this value to instruct the kernel to use the second partition of MMC block device 0 as its root partition:

```
UBOOT_EXTLINUX_ROOT = "root=/dev/mmcblk0p2"
```

### `UBOOT_EXTLINUX_TIMEOUT`

When inheriting the `uboot-extlinux-config` class, the `UBOOT_EXTLINUX_TIMEOUT` variable is optional and sets the value of the `TIMEOUT` property of the `extlinux.conf` file used for booting.

### `UBOOT_FIT_ADDRESS_CELLS`

Specifies the value of the `#address-cells` value for the description of the U-Boot FIT image.

The default value is set to "1" by the `uboot-sign` class, which corresponds to 32 bit addresses.

For platforms that need to set 64 bit addresses in `UBOOT_LOADADDRESS` and `UBOOT_ENTRYPOINT`, you need to set this value to "2", as two 32 bit values (cells) will be needed to represent such addresses.

Here is an example setting "0x400000000" as a load address:

```
UBOOT_FIT_ADDRESS_CELLS = "2"
UBOOT_LOADADDRESS = "0x04 0x00000000"
```

See more details about `#address-cells`.

### ***UBOOT\_FIT\_ARM\_TRUSTED\_FIRMWARE***

Trusted Firmware-A (TF-A) is a reference implementation of secure world software for Arm A-Profile architectures (Armv8-A and Armv7-A), including an Exception Level 3 (EL3) Secure Monitor. This variable enables the generation of a U-Boot FIT image with a Trusted Firmware-A (TF-A) binary.

Its default value is "0", so set it to "1" to enable this functionality:

```
UBOOT_FIT_ARM_TRUSTED_FIRMWARE = "1"
```

### ***UBOOT\_FIT\_ARM\_TRUSTED\_FIRMWARE\_IMAGE***

Specifies the path to the Trusted Firmware-A (TF-A) binary. Its default value is "bl31.bin":

```
UBOOT_FIT_ARM_TRUSTED_FIRMWARE_IMAGE ?= "bl31.bin"
```

If a relative path is provided, the file is expected to be relative to U-Boot's *B* directory. An absolute path can be provided too, e.g.:

```
UBOOT_FIT_ARM_TRUSTED_FIRMWARE_IMAGE ?= "${DEPLOY_DIR_IMAGE}/bl31.bin"
```

If the Trusted Firmware-A (TF-A) binary is built in a separate recipe, you must add the necessary dependency in a U-Boot `.bbappend` file. The recipe name for Trusted Firmware-A (TF-A) binary is `trusted-firmware-a`, which comes from the [meta-arm](#) layer:

```
do_compile[depends] += "trusted-firmware-a:do_deploy"
```

### ***UBOOT\_FIT\_CONF\_DESC***

The `UBOOT_FIT_CONF_DESC` can be set to override the description property of the configuration node of a U-Boot FIT image.

### ***UBOOT\_FIT\_CONF\_FIRMWARE***

Adds one image to the `firmware` property of the configuration node of the U-Boot Image Tree Source (ITS). Sets the `firmware` property to select the image to boot first:

```
UBOOT_FIT_CONF_FIRMWARE = "fwa"
```

If not set, the first entry in "loadables" is used to boot instead.

### ***UBOOT\_FIT\_CONF\_USER\_LOADABLES***

Adds one or more user-defined images to the `loadables` property of the configuration node of the U-Boot Image Tree Source (ITS). This variable is handled by the local shell in the recipe so appropriate escaping should be done, e.g. escaping quotes.:

```
UBOOT_FIT_CONF_USER_LOADABLES = '\"fwa\", \"fwb\"'
```

### ***UBOOT\_FIT\_DESC***

Specifies the description string encoded into a U-Boot fitImage. The default value is set by the `uboot-sign` class as follows:

```
UBOOT_FIT_DESC ?= "U-Boot fitImage for ${DISTRO_NAME}/${PV}/${MACHINE}"
```

### ***UBOOT\_FIT\_GENERATE\_KEYS***

Decides whether to generate the keys for signing the U-Boot fitImage if they don't already exist. The keys are created in *SPL\_SIGN\_KEYDIR*. The default value is "0".

Enable this as follows:

```
UBOOT_FIT_GENERATE_KEYS = "1"
```

This variable is used in the *uboot-sign* class.

### ***UBOOT\_FIT\_HASH\_ALG***

Specifies the hash algorithm used in creating the U-Boot FIT Image. It is set by default to `sha256` by the *uboot-sign* class.

### ***UBOOT\_FIT\_KEY\_GENRSA\_ARGS***

Arguments to `openssl genrsa` for generating a RSA private key for signing the U-Boot FIT image. The default value of this variable is set to "-F4" by the *uboot-sign* class.

### ***UBOOT\_FIT\_KEY\_REQ\_ARGS***

Arguments to `openssl req` for generating a certificate for signing the U-Boot FIT image. The default value is "-batch -new" by the *uboot-sign* class, "batch" for non interactive mode and "new" for generating new keys.

### ***UBOOT\_FIT\_KEY\_SIGN\_PKCS***

Format for the public key certificate used for signing the U-Boot FIT image. The default value is set to "x509" by the *uboot-sign* class.

### ***UBOOT\_FIT\_SIGN\_ALG***

Specifies the signature algorithm used in creating the U-Boot FIT Image. This variable is set by default to "rsa2048" by the *uboot-sign* class.

### ***UBOOT\_FIT\_SIGN\_NUMBITS***

Size of the private key used in signing the U-Boot FIT image, in number of bits. The default value for this variable is set to "2048" by the *uboot-sign* class.

### ***UBOOT\_FIT\_TEE***

A Trusted Execution Environment (TEE) is a secure environment for executing code, ensuring high levels of trust in asset management within the surrounding system. This variable enables the generation of a U-Boot FIT image with a Trusted Execution Environment (TEE) binary.

Its default value is "0", so set it to "1" to enable this functionality:

```
UBOOT_FIT_TEE = "1"
```

### ***UBOOT\_FIT\_TEE\_IMAGE***

Specifies the path to the Trusted Execution Environment (TEE) binary. Its default value is "tee-raw.bin":

```
UBOOT_FIT_TEE_IMAGE ?= "tee-raw.bin"
```

If a relative path is provided, the file is expected to be relative to U-Boot's *B* directory. An absolute path can be provided too, e.g.:

```
UBOOT_FIT_TEE_IMAGE ?= "${DEPLOY_DIR_IMAGE}/tee-raw.bin"
```

If the Trusted Execution Environment (TEE) binary is built in a separate recipe, you must add the necessary dependency in a U-Boot `.bbappend` file. The recipe name for Trusted Execution Environment (TEE) binary is `optee-os`, which comes from the `meta-arm` layer:

```
do_compile[depends] += "optee-os:do_deploy"
```

### UBOOT\_FIT\_USER\_SETTINGS

Add a user-specific snippet to the U-Boot Image Tree Source (ITS). This variable allows the user to add one or more user-defined `/images` node to the U-Boot Image Tree Source (ITS). For more details, please refer to <https://fitspec.osfw.foundation/>.

The original content of the U-Boot Image Tree Source (ITS) is as follows:

```
images {
    uboot {
        description = "U-Boot image";
        data = /incbin/("u-boot-nodtb.bin");
        type = "standalone";
        os = "u-boot";
        arch = "";
        compression = "none";
        load = <0x80000000>;
        entry = <0x80000000>;
    };
};
```

Users can include their custom ITS snippet in this variable, e.g.:

```
UBOOT_FIT_FWA_ITS = '\n
    fwa {\n\n
        description = \"FW A\";\n\n
        data = /incbin/(\"fwa.bin\");\n\n
        type = \"firmware\";\n\n
        arch = \"\";\n\n
        os = \"\";\n\n
        load = <0xb2000000>;\n\n
        entry = <0xb2000000>;\n\n
        compression = \"none\";\n\n
    };\n\n
'
```

(continues on next page)

(continua dalla pagina precedente)

```
UBOOT_FIT_USER_SETTINGS = "${UBOOT_FIT_FWA_ITS}"
```

This variable is handled by the local shell in the recipe so appropriate escaping should be done, e.g. escaping quotes and adding newlines with `\n`.

The generated content of the U-Boot Image Tree Source (ITS) is as follows:

```
images {
    uboot {
        description = "U-Boot image";
        data = /incbin/"u-boot-nodtb.bin";
        type = "standalone";
        os = "u-boot";
        arch = "";
        compression = "none";
        load = <0x80000000>;
        entry = <0x80000000>;
    };
    fwa {
        description = "FW A";
        data = /incbin/"fwa.bin";
        type = "firmware";
        arch = "";
        os = "";
        load = <0xb2000000>;
        entry = <0xb2000000>;
        compression = "none";
    };
};
```

### ***UBOOT\_FITIMAGE\_ENABLE***

This variable allows to generate a FIT image for U-Boot, which is one of the ways to implement a verified boot process.

Its default value is "0", so set it to "1" to enable this functionality:

```
UBOOT_FITIMAGE_ENABLE = "1"
```

See the *uboot-sign* class for details.

### ***UBOOT\_FRAGMENTS***

The *UBOOT\_FRAGMENTS* variable can be used to pass extra config fragments from the source tree to make when U-Boot is configured. These fragments are located in same `${S}/configs/` directory as the `defconfig`.

Per esempio:



```
UBOOT_MACHINE = "am62x_evm_r5_defconfig"
UBOOT_FRAGMENTS = "am62x_r5_usbdfu.config"
```

See the *uboot-config* class for more information.

### UBOOT\_INITIAL\_ENV\_BINARY

This variable enables the generation of the U-Boot initial environment in binary format.

Its default value is "0", set it to "1" to enable this functionality:

```
UBOOT_INITIAL_ENV_BINARY = "1"
```

If set to "1", you must also set the size of the environment with *UBOOT\_INITIAL\_ENV\_BINARY\_SIZE*.

This variable is used in the *uboot-config* class.

The resulting binary can be flashed using *WIC* or any other flashing method at the environment offset, overriding any existing environment if one is present. Below is an example of a WKS file to flash the binary:

```
part --source rawcopy --sourceparams="file=u-boot-initial-env-sd.bin" --ondisk.
↳ sda --no-table --offset 4096k
```

In this example, the U-Boot initial environment binary *u-boot-initial-env-sd.bin* is flashed at offset 4096 kibibyte.

### UBOOT\_INITIAL\_ENV\_BINARY\_REDUND

If redundant environment support is enabled in U-boot's configuration, this variable should be set to properly generate the redundant environment in the output U-boot environment binary file.

Its default value is "0", set it to "1" to enable this functionality:

```
UBOOT_INITIAL_ENV_BINARY_REDUND = "1"
```

The *UBOOT\_INITIAL\_ENV\_BINARY* must also be set to "1" if *UBOOT\_INITIAL\_ENV\_BINARY\_REDUND* is enabled.

This variable is used in the *uboot-config* class.

### UBOOT\_INITIAL\_ENV\_BINARY\_SIZE

This variable sets the binary size (in bytes) of the U-Boot initial environment. Both hexadecimal and decimal values are supported and can be set as follows:

```
UBOOT_INITIAL_ENV_BINARY_SIZE = "0x4000"
```

This variable is used in the *uboot-config* class.

### UBOOT\_LOADADDRESS

Specifies the load address for the U-Boot image. During U-Boot image creation, the *UBOOT\_LOADADDRESS* variable is passed as a command-line parameter to the *uboot-mkimage* utility.

To pass a 64 bit address, you will also need to set:

- The *FIT\_ADDRESS\_CELLS* variable for FIT image creation.

- The `UBOOT_FIT_ADDRESS_CELLS` variable for U-Boot FIT image creation.

This variable is used by the `kernel-fit-image`, `kernel-uimage`, `kernel`, `uboot-config` and `uboot-sign` classes.

### **`UBOOT_LOCALVERSION`**

Appends a string to the name of the local version of the U-Boot image. For example, assuming the version of the U-Boot image built was "2013.10", the full version string reported by U-Boot would be "2013.10-yocto" given the following statement:

```
UBOOT_LOCALVERSION = "-yocto"
```

### **`UBOOT_MACHINE`**

Specifies the value passed on the `make` command line when building a U-Boot image. The value indicates the target platform configuration. You typically set this variable from the machine configuration file (i.e. `conf/machine/machine_name.conf`).

Please see the "Selection of Processor Architecture and Board Type" section in the U-Boot README for valid values for this variable.

### **`UBOOT_MAKE_OPTS`**

The `UBOOT_MAKE_OPTS` variable can be used to pass extra options to `make` when U-Boot is configured and compiled.

See the `uboot-config` class for more information.

### **`UBOOT_MAKE_TARGET`**

Specifies the target called in the `Makefile`. The default target is "all".

### **`UBOOT_MKIMAGE`**

Specifies the name of the `mkimage` command as used by the `kernel-fit-image` class to assemble the FIT image. This can be used to substitute an alternative command, wrapper script or function if desired. The default is "uboot-mkimage".

### **`UBOOT_MKIMAGE_DTCOPTS`**

Options for the device tree compiler passed to `mkimage -D` feature while creating a FIT image with the `kernel-fit-image` class. If `UBOOT_MKIMAGE_DTCOPTS` is not set then the `kernel-fit-image` class will not pass the `-D` option to `mkimage`.

This variable is also used by the `uboot-sign` class.

### **`UBOOT_MKIMAGE_KERNEL_TYPE`**

Specifies the type argument for the kernel as passed to `uboot-mkimage`. The default value is "kernel".

### **`UBOOT_MKIMAGE_SIGN`**

Specifies the name of the `mkimage` command as used by the `kernel-fit-image` class to sign the FIT image after it has been assembled (if enabled). This can be used to substitute an alternative command, wrapper script or function if desired. The default is "\${`UBOOT_MKIMAGE`}".

### **`UBOOT_MKIMAGE_SIGN_ARGS`**

Optionally specifies additional arguments for the `kernel-fit-image` class to pass to the `mkimage` command when signing the FIT image.

### ***UBOOT\_RD\_ENTRYPOINT***

Specifies the entrypoint for the RAM disk image. During FIT image creation, the *UBOOT\_RD\_ENTRYPOINT* variable is used in *kernel-fit-image* class to specify the entrypoint to be used in creating the Image Tree Source for the FIT image.

### ***UBOOT\_RD\_LOADADDRESS***

Specifies the load address for the RAM disk image. During FIT image creation, the *UBOOT\_RD\_LOADADDRESS* variable is used in *kernel-fit-image* class to specify the load address to be used in creating the Image Tree Source for the FIT image.

### ***UBOOT\_SIGN\_ENABLE***

Enable signing of FIT image. The default value is "0".

This variable is defined and used by *uboot-config* class.

Additionally, it serves as the default value for the *FIT\_KERNEL\_SIGN\_ENABLE* variable, which is used by the *kernel-fit-image* class.

That means, if *UBOOT\_SIGN\_ENABLE* is set to "1", the *kernel-fit-image* class will sign the FIT image at build-time using the specified private key, and the *uboot-sign* class will inject the corresponding public key into U-Boot's device tree. This makes U-Boot verify the authenticity and integrity of the FIT image at boot time, providing a secure boot workflow that helps prevent unauthorized or tampered images from being loaded.

See <https://docs.u-boot.org/en/v2025.10/usage/fit/signature.html> for more information on FIT signature verification in U-Boot.

### ***UBOOT\_SIGN\_KEYDIR***

Location of the directory containing the RSA key and certificate used for signing the FIT image, used by the *kernel-fit-image* (via the *FIT\_KERNEL\_SIGN\_KEYDIR* variable) and *uboot-sign* classes.

### ***UBOOT\_SIGN\_KEYNAME***

The name of keys used by the *kernel-fit-image* class (via the *FIT\_KERNEL\_SIGN\_KEYNAME* variable) for signing U-Boot FIT image stored in the *UBOOT\_SIGN\_KEYDIR* directory. If we have for example a *dev.* key key and a *dev.crt* certificate stored in the *UBOOT\_SIGN\_KEYDIR* directory, you will have to set *UBOOT\_SIGN\_KEYNAME* to *dev.*

### ***UBOOT\_SUFFIX***

Points to the generated U-Boot extension. For example, *u-boot.sb* has a *.sb* extension.

The default U-Boot extension is *.bin*

### ***UBOOT\_TARGET***

Specifies the target used for building U-Boot. The target is passed directly as part of the "make" command (e.g. SPL and AIS). If you do not specifically set this variable, the OpenEmbedded build process passes and uses "all" for the target during the U-Boot building process.

### ***UBOOT\_VERSION***

When naming the files that are installed and deployed, the package version (*PV*) and revision (*PR*) are part of the filename. The *UBOOT\_VERSION* variable contains this information, but can be overridden if desired.

### ***UKI\_CMDLINE***

When inheriting the *uki* class, the kernel command line to use when booting the Unified Kernel Image (UKI). Defaults to `rootwait root=LABEL=root console=${KERNEL_CONSOLE}`.

### ***UKI\_CONFIG\_FILE***

When inheriting the *uki* class, an optional config file for the *ukify* command.

### ***UKI\_DEVICETREE***

When inheriting the *uki* class, the *UKI\_DEVICETREE* variable holds the list of device tree blobs to include in the Unified Kernel Image (UKI).

### ***UKI\_FILENAME***

When inheriting the *uki* class, the output file name for the generated Unified Kernel Image (UKI). Defaults to *uki.efi*.

### ***UKI\_KERNEL\_FILENAME***

When inheriting the *uki* class, the kernel image file name to use as input. Defaults to *KERNEL\_IMAGETYPE*.

### ***UKI\_SB\_CERT***

When inheriting the *uki* class, optional UEFI secureboot certificate matching the private key in *UKI\_SB\_KEY*.

### ***UKI\_SB\_KEY***

When inheriting the *uki* class, optional UEFI secureboot private key to sign the Unified Kernel Image (UKI).

### ***UKIFY\_CMD***

When inheriting the *uki* class, *ukify* command to build Unified Kernel Image (UKI). Defaults to *ukify build*.

### ***UNINATIVE\_CHECKSUM***

When inheriting the *uninative* class, the *UNINATIVE\_CHECKSUM* variable flags contain the checksums of the uninative tarball as specified by the *UNINATIVE\_URL* variable. There should be one checksum per tarballs published at *UNINATIVE\_URL*, which match architectures. For example:

```
UNINATIVE_CHECKSUM[aarch64] ?=
→ "812045d826b7fda88944055e8526b95a5a9440bfef608d5b53fd52faab49bf85"
UNINATIVE_CHECKSUM[i686] ?=
→ "5cc28efd0c15a75de4bcb147c6cce65f1c1c9d442173a220f08427f40a3ffa09"
UNINATIVE_CHECKSUM[x86_64] ?=
→ "4c03d1ed2b7b4e823aca4a1a23d8f2e322f1770fc10e859adced5777aff4f3a"
```

### ***UNINATIVE\_URL***

When inheriting the *uninative* class, the *UNINATIVE\_URL* variable contains the URL where the uninative tarballs are published.

### ***UNKNOWN\_CONFIGURE\_OPT\_IGNORE***

Specifies a list of options that, if reported by the configure script as being invalid, should not generate a warning during the *do\_configure* task. Normally, invalid configure options are simply not passed to the configure script (e.g. should be removed from *EXTRA\_OECONF* or *PACKAGECONFIG\_CONFARGS*). However, there are common options that are passed to all configure scripts at a class level, but might not be valid for some configure scripts. Therefore warnings about these options are useless. For these cases, the options are added to *UNKNOWN\_CONFIGURE\_OPT\_IGNORE*.

The configure arguments check that uses *UNKNOWN\_CONFIGURE\_OPT\_IGNORE* is part of the *insane* class and is only enabled if the recipe inherits the *autotools\** class.

### UNPACKDIR

This variable, used by the *base* class, specifies where fetched sources should be unpacked by the *do\_unpack* task.

### UPDATERCPN

For recipes inheriting the *update-rc.d* class, *UPDATERCPN* specifies the package that contains the initscript that is enabled.

The default value is "\${PN}". Given that almost all recipes that install initscripts package them in the main package for the recipe, you rarely need to set this variable in individual recipes.

### UPSTREAM\_CHECK\_COMMITS

You can perform a per-recipe check for what the latest upstream source code version is by calling `devtool latest-version recipe`. If the recipe source code is provided from Git repositories, but releases are not identified by Git tags, set *UPSTREAM\_CHECK\_COMMITS* to 1 in the recipe, and the OpenEmbedded build system will compare the latest commit with the one currently specified by the recipe (*SRCREV*):

```
UPSTREAM_CHECK_COMMITS = "1"
```

### UPSTREAM\_CHECK\_GITTAGREGEX

You can perform a per-recipe check for what the latest upstream source code version is by calling `devtool latest-version recipe`. If the recipe source code is provided from Git repositories, the OpenEmbedded build system determines the latest upstream version by picking the latest tag from the list of all repository tags.

You can use the *UPSTREAM\_CHECK\_GITTAGREGEX* variable to provide a regular expression to filter only the relevant tags should the default filter not work correctly:

```
UPSTREAM_CHECK_GITTAGREGEX = "git_tag_regex"
```

### UPSTREAM\_CHECK\_REGEX

Use the *UPSTREAM\_CHECK\_REGEX* variable to specify a different regular expression instead of the default one when the package checking system is parsing the page found using *UPSTREAM\_CHECK\_URI*:

```
UPSTREAM_CHECK_REGEX = "package_regex"
```

### UPSTREAM\_CHECK\_URI

You can perform a per-recipe check for what the latest upstream source code version is by calling `devtool latest-version recipe`. If the source code is provided from tarballs, the latest version is determined by fetching the directory listing where the tarball is and attempting to find a later tarball. When this approach does not work, you can use *UPSTREAM\_CHECK\_URI* to provide a different URI that contains the link to the latest tarball:

```
UPSTREAM_CHECK_URI = "recipe_url"
```

### UPSTREAM\_STABLE\_RELEASE\_REGEX

A regular expression used to filter upstream versions during version checks so that only versions within the same stable series are considered. When set, BitBake's fetchers (git, wget, crate) apply this regex to discovered upstream versions and discard any that do not match.

For example, if a recipe is at version 1.4.2 and the regex is `^1\.4(\.\d+)*$`, then 1.4.7 would be a valid upgrade candidate but 1.5.0 would not.

For recipes with dot-separated versions, inherit the *upstream-stable-release-point* class to generate this variable automatically. For other versioning schemes, set it directly:

```
UPSTREAM_STABLE_RELEASE_REGEX = "^10\.2p\d+$"
```

See *Aggiornamenti a Release Stabili* for the criteria under which this variable should be set.

### UPSTREAM\_VERSION\_UNKNOWN

You can perform a per-recipe check for what the latest upstream source code version is by calling `devtool latest-version recipe`. If no combination of the *UPSTREAM\_CHECK\_URI*, *UPSTREAM\_CHECK\_REGEX*, *UPSTREAM\_CHECK\_GITTAGREGEX* and *UPSTREAM\_CHECK\_COMMITS* variables in the recipe allows to determine what the latest upstream version is, you can set *UPSTREAM\_VERSION\_UNKNOWN* to 1 in the recipe to acknowledge that the check cannot be performed:

```
UPSTREAM_VERSION_UNKNOWN = "1"
```

### USE\_DEVFS

Determines if `devtmpfs` is used for `/dev` population. The default value used for *USE\_DEVFS* is "1" when no value is specifically set. Typically, you would set *USE\_DEVFS* to "0" for a statically populated `/dev` directory.

See the "*Selecting a Device Manager*" section in the Yocto Project Development Tasks Manual for information on how to use this variable.

### USE\_NLS

Determine if language translations should be built for recipes that can build them. This variable can be equal to:

- `yes`: translations are enabled.
- `no`: translation are disabled.

Recipes can use the value of this variable to enable language translations in their build. Classes such as *gettext* use the value of this variable to enable *Gettext* support.

### USE\_VT

When using *SysVinit*, determines whether or not to run a *getty* on any virtual terminals in order to enable logging in through those terminals.

The default value used for *USE\_VT* is "1" when no default value is specifically set. Typically, you would set *USE\_VT* to "0" in the machine configuration file for machines that do not have a graphical display attached and therefore do not need virtual terminal functionality.

### USER\_CLASSES

A list of classes to globally inherit. These classes are used by the OpenEmbedded build system to enable extra features.

Classes inherited using *USER\_CLASSES* must be located in the `classes-global/` or `classes/` subdirectories.

A default list is set in the `meta/conf/templates/default/local.conf.sample` file:

```
USER_CLASSES ?= "buildstats"
```

### ***USERADD\_DEPENDS***

Specifies a list of recipes that create users / groups (via *USERADD\_PARAM* / *GROUPADD\_PARAM*) which a recipe depends upon. This ensures that those users / groups are available when building a recipe.

### ***USERADD\_ERROR\_DYNAMIC***

If set to `error`, forces the OpenEmbedded build system to produce an error if the user identification (`uid`) and group identification (`gid`) values are not defined in any of the files listed in *USERADD\_UID\_TABLES* and *USERADD\_GID\_TABLES*. If set to `warn`, a warning will be issued instead.

The default behavior for the build system is to dynamically apply `uid` and `gid` values. Consequently, the *USERADD\_ERROR\_DYNAMIC* variable is by default not set. If you plan on using statically assigned `gid` and `uid` values, you should set the *USERADD\_ERROR\_DYNAMIC* variable in a *configuration file*:

```
USERADD_ERROR_DYNAMIC = "error"
```

Overriding the default behavior implies you are going to also take steps to set static `uid` and `gid` values through use of the *USERADDEXTENSION*, *USERADD\_UID\_TABLES*, and *USERADD\_GID\_TABLES* variables.

#### **Nota**

There is a difference in behavior between setting *USERADD\_ERROR\_DYNAMIC* to `error` and setting it to `warn`. When it is set to `warn`, the build system will report a warning for every undefined `uid` and `gid` in any recipe. But when it is set to `error`, it will only report errors for recipes that are actually built. This saves you from having to add static IDs for recipes that you know will never be built.

### ***USERADD\_GID\_TABLES***

Specifies a password file to use for obtaining static group identification (`gid`) values when the OpenEmbedded build system adds a group to the system during package installation.

When applying static group identification (`gid`) values, the OpenEmbedded build system looks in *BBPATH* for a `files/group` file and then applies those `uid` values. Set the variable as follows in a *configuration file*:

```
USERADD_GID_TABLES = "files/group"
```

#### **Nota**

Setting the *USERADDEXTENSION* variable to `"useradd-staticids"` causes the build system to use static `gid` values.

### ***USERADD\_PACKAGES***

When inheriting the *useradd\** class, this variable specifies the individual packages within the recipe that require users and/or groups to be added.

You must set this variable if the recipe inherits the class. For example, the following enables adding a user for the main package in a recipe:

```
USERADD_PACKAGES = "${PN}"
```

**i Nota**

It follows that if you are going to use the `USERADD_PACKAGES` variable, you need to set one or more of the `USERADD_PARAM`, `GROUPADD_PARAM`, or `USERMOD_PARAM` variables.

### `USERADD_PARAM`

When inheriting the `useradd*` class, this variable specifies for a package what parameters should pass to the `useradd` command if you add a user to the system when the package is installed.

Here is an example from the `dbus` recipe:

```
USERADD_PARAM:${PN} = "--system --home ${localstatedir}/lib/dbus \  
                        --no-create-home --shell /bin/false \  
                        --user-group messagebus"
```

For information on the standard Linux shell command `useradd`, see `useradd(8)`.

### `USERADD_UID_TABLES`

Specifies a password file to use for obtaining static user identification (`uid`) values when the OpenEmbedded build system adds a user to the system during package installation.

When applying static user identification (`uid`) values, the OpenEmbedded build system looks in `BBPATH` for a `files/passwd` file and then applies those `uid` values. Set the variable as follows in a *configuration file*:

```
USERADD_UID_TABLES = "files/passwd"
```

**i Nota**

Setting the `USERADDEXTENSION` variable to "useradd-staticids" causes the build system to use static `uid` values.

### `USERADDEXTENSION`

When set to "useradd-staticids", causes the OpenEmbedded build system to base all user and group additions on a static `passwd` and `group` files found in `BBPATH`.

To use static user identification (`uid`) and group identification (`gid`) values, set the variable as follows in in a *configuration file*:

```
USERADDEXTENSION = "useradd-staticids"
```



**Nota**

Setting this variable to use static `uid` and `gid` values causes the OpenEmbedded build system to employ the `useradd*` class.

If you use static `uid` and `gid` information, you must also specify the `files/passwd` and `files/group` files by setting the `USERADD_UID_TABLES` and `USERADD_GID_TABLES` variables. Additionally, you should also set the `USERADD_ERROR_DYNAMIC` variable.

**USERMOD\_PARAM**

When a recipe inherits the `useradd*` class, this variable specifies for a package what parameters should be passed to the `usermod` command if you wish to modify a user when the package is installed. It is typically used to add the user to one or more groups. For example:

```
USERMOD_PARAM:${PN} = "--append --groups group1,group2 user"
```

**VIRTUAL-RUNTIME**

`VIRTUAL-RUNTIME` is a commonly used prefix for defining virtual packages for runtime usage, typically for use in `RDEPENDS` or in image definitions.

An example is `VIRTUAL-RUNTIME_base-utils` that makes it possible to either use BusyBox based utilities:

```
VIRTUAL-RUNTIME_base-utils = "busybox"
```

or their full featured implementations from GNU Coreutils and other projects:

```
VIRTUAL-RUNTIME_base-utils = "packagegroup-core-base-utils"
```

Here are two examples using this virtual runtime package. The first one is in `initramfs-framework_1.0.bb`:

```
RDEPENDS:${PN} += "${VIRTUAL-RUNTIME_base-utils}"
```

The second example is in the `core-image-initramfs-boot` image definition:

```
PACKAGE_INSTALL = "${INITRAMFS_SCRIPTS} ${VIRTUAL-RUNTIME_base-utils} base-  
↪passwd"
```

**WARN\_QA**

Specifies the quality assurance checks whose failures are reported as warnings by the OpenEmbedded build system. You set this variable in your distribution configuration file. For a list of the checks you can control with this variable, see the `"insane"` section.

**WATCHDOG\_RUNTIME\_SEC**

For the `systemd` recipe, this controls the value of the `RuntimeWatchdogSec` option in `/etc/systemd/system.conf`. The default value is an empty string.

**WATCHDOG\_TIMEOUT**

Specifies the timeout in seconds used by the `watchdog-config` recipe and also by `systemd` during reboot. The default is 60 seconds.

### WESTON\_USER

The `WESTON_USER` variable defines the username for the *Weston* user.

### WESTON\_USER\_HOME

The `WESTON_USER` variable defines the path to the home directory for the *Weston* user.

### WIC\_CREATE\_EXTRA\_ARGS

If the `IMAGE_FSTYPES` variable contains "wic", the build will generate a *Wic image* automatically when BitBake builds an image recipe. As part of this process BitBake will invoke the "wic create" command. The `WIC_CREATE_EXTRA_ARGS` variable is placed at the end of this command which allows the user to supply additional arguments.

One such useful purpose for this mechanism is to add the `-D` (or `--debug`) argument to the "wic create" command. This increases the amount of debugging information written out to the Wic log during the Wic creation process.

### WIC\_SECTOR\_SIZE

#### **Avvertimento**

This variable is deprecated in favor of the `--sector-size wic` command-line argument. See *WIC\_SECTOR\_SIZE should be replaced by --sector-size* for more information.

The variable `WIC_SECTOR_SIZE` controls the sector size of Wic images. In the background, this controls the value of the `PARTED_SECTOR_SIZE` environment variable passed to the `parted` command-line utility, used to generate the images. The default value is 512.

For more information on how to create Wic images, see the "*Creating Partitioned Images Using Wic*" section in the Yocto Project Development Tasks Manual.

### WIRELESS\_DAEMON

For `connman` and `packagegroup-base`, specifies the wireless daemon to use. The default is "wpa-supPLICANT" (note that the value uses a dash and not an underscore).

### WKS\_FILE

Specifies the location of the Wic kickstart file that is used by the OpenEmbedded build system to create a partitioned image (`image.wic`). For information on how to create a partitioned image, see the "*Creating Partitioned Images Using Wic*" section in the Yocto Project Development Tasks Manual. For details on the kickstart file format, see the "*OpenEmbedded Kickstart (.wks) Reference*" Chapter.

### WKS\_FILE\_DEPENDS

When placed in the recipe that builds your image, this variable lists build-time dependencies. The `WKS_FILE_DEPENDS` variable is only applicable when Wic images are active (i.e. when `IMAGE_FSTYPES` contains entries related to Wic). If your recipe does not create Wic images, the variable has no effect.

The `WKS_FILE_DEPENDS` variable is similar to the `DEPENDS` variable. When you use the variable in your recipe that builds the Wic image, dependencies you list in the `WKS_FILE_DEPENDS` variable are added to the `DEPENDS` variable.

With the `WKS_FILE_DEPENDS` variable, you have the possibility to specify a list of additional dependencies (e.g. native tools, bootloaders, and so forth), that are required to build Wic images. Here is an example:

```
WKS_FILE_DEPENDS = "some-native-tool"
```

In the previous example, `some-native-tool` would be replaced with an actual native tool on which the build would depend.

### WKS\_FILES

Specifies a list of candidate Wic kickstart files to be used by the OpenEmbedded build system to create a partitioned image. Only the first one that is found, from left to right, will be used.

This is only useful when there are multiple `.wks` files that can be used to produce an image. A typical case is when multiple layers are used for different hardware platforms, each supplying a different `.wks` file. In this case, you specify all possible ones through `WKS_FILES`.

If only one `.wks` file is used, set `WKS_FILE` instead.

### WORKDIR

The pathname of the work directory in which the OpenEmbedded build system builds a recipe. This directory is located within the `TMPDIR` directory structure and is specific to the recipe being built and the system for which it is being built.

The `WORKDIR` directory is defined as follows:

```
${TMPDIR}/work/${MULTIMACH_TARGET_SYS}/${PN}/${EXTENDPE}${PV}-${PR}
```

The actual directory depends on several things:

- `TMPDIR`: The top-level build output directory
- `MULTIMACH_TARGET_SYS`: The target system identifier
- `PN`: The recipe name
- `EXTENDPE`: The epoch --- if `PE` is not specified, which is usually the case for most recipes, then `EXTENDPE` is blank.
- `PV`: The recipe version
- `PR`: The recipe revision

As an example, assume a Source Directory top-level folder name `bitbake-builds`, a default *Build Directory* at `bitbake-builds/build`, and a `qemux86-poky-linux` machine target system. Furthermore, suppose your recipe is named `foo_1.3.0-r0.bb`. In this case, the work directory the build system uses to build the package would be as follows:

```
bitbake-builds/build/tmp/work/qemux86-poky-linux/foo/1.3.0-r0
```

### XSERVER

Specifies the packages that should be installed to provide an X server and drivers for the current machine, assuming your image directly includes `packagegroup-core-x11-xserver` or, perhaps indirectly, includes "x11-base" in `IMAGE_FEATURES`.

The default value of `XSERVER`, if not specified in the machine configuration, is `"xserver-xorg xf86-video-fbdev xf86-input-evdev"`.

### *XZ\_MEMLIMIT*

Specifies the maximum memory the xz compression should use as a percentage of system memory. If unconstrained the xz compressor can use large amounts of memory and become problematic with parallelism elsewhere in the build. "50%" has been found to be a good value.

### *XZ\_THREADS*

Specifies the number of parallel threads that should be used when using xz compression.

By default this scales with core count, but is never set less than 2 to ensure that multi-threaded mode is always used so that the output file contents are deterministic. Builds will work with a value of 1 but the output will differ compared to the output from the compression generated when more than one thread is used.

On systems where many tasks run in parallel, setting a limit to this can be helpful in controlling system resource usage.

### *ZSTD\_COMPRESSION\_LEVEL*

Specifies the compression level to be used with ZStandard compression (from 1 to 19, set to 3 by default, following upstream choice). Higher levels produce smaller files, but take longer to complete.

### *ZSTD\_THREADS*

Specifies the number of parallel threads that should be used when using ZStandard compression.

By default this scales with core count, but is never set less than 2 to ensure that multi-threaded mode is always used so that the output file contents are deterministic. Builds will work with a value of 1 but the output will differ compared to the output from the compression generated when more than one thread is used.

On systems where many tasks run in parallel, setting a limit to this can be helpful in controlling system resource usage.

## 6.15 Variable Context

While you can use most variables in almost any context such as `.conf`, `.bbclass`, `.inc`, and `.bb` files, some variables are often associated with a particular locality or context. This chapter describes some common associations.

### 6.15.1 Configuration

The following subsections provide lists of variables whose context is configuration: distribution, machine, and local.

#### Distribution (Distro)

This section lists variables whose configuration context is the distribution, or distro.

- *DISTRO*
- *DISTRO\_NAME*
- *DISTRO\_VERSION*
- *MAINTAINER*
- *PACKAGE\_CLASSES*
- *TARGET\_OS*

- *TARGET\_FPU*
- *TCMODE*
- *TCLIBC*

## Machine

This section lists variables whose configuration context is the machine.

- *TARGET\_ARCH*
- *SERIAL\_CONSOLES*
- *PACKAGE\_EXTRA\_ARCHS*
- *IMAGE\_FSTYPES*
- *MACHINE\_FEATURES*
- *MACHINE\_EXTRA\_RDEPENDS*
- *MACHINE\_EXTRA\_RRECOMMENDS*
- *MACHINE\_ESSENTIAL\_EXTRA\_RDEPENDS*
- *MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS*

## Local

This section lists variables whose configuration context is the local configuration through the *build/conf/local.conf* file.

- *DISTRO* (can also be set by the *distro/* built-in fragment)
- *MACHINE* (can also be set by the *machine/* built-in fragment)
- *DL\_DIR*
- *EXTRA\_IMAGE\_FEATURES*
- *PACKAGE\_CLASSES*
- *BB\_NUMBER\_THREADS*
- *BBINCLUDELOGS*
- *ENABLE\_BINARY\_LOCALE\_GENERATION*

### 6.15.2 Ricette

The following subsections provide lists of variables whose context is recipes: required, dependencies, path, and extra build information.

## Required

This section lists variables that are required for recipes.

- *LICENSE*
- *LIC\_FILES\_CHKSUM*
- *SRC\_URI* --- used in recipes that fetch local or remote files.

## Dependencies

This section lists variables that define recipe dependencies.

- *DEPENDS*
- *RDEPENDS*
- *RRECOMMENDS*
- *RCONFLICTS*
- *RREPLACES*

## Paths

This section lists variables that define recipe paths.

- *WORKDIR*
- *S*
- *FILES*

## Extra Build Information

This section lists variables that define extra build information for recipes.

- *DEFAULT\_PREFERENCE*
- *EXTRA\_OECMAKE*
- *EXTRA\_OECONF*
- *EXTRA\_OEMAKE*
- *PACKAGECONFIG\_CONFARGS*
- *PACKAGES*

## 6.16 FAQ

### Indice

- *FAQ*

– *General questions*

- \* *How does Poky differ from OpenEmbedded?*
- \* *How can you claim Poky / OpenEmbedded-Core is stable?*
- \* *Are there any products built using the OpenEmbedded build system?*
- \* *Why isn't systemd the default init system in the Poky distro?*

– *Building environment*

- \* *Missing dependencies on the development system?*
- \* *How does OpenEmbedded fetch source code? Will it work through a firewall or proxy server?*

– *Using the OpenEmbedded Build system*

- \* *How do I use an external toolchain?*
- \* *Why do I get chmod permission issues?*
- \* *I see many 404 errors trying to download sources. Is anything wrong?*
- \* *Why do I get random build failures?*
- \* *Why does the build fail with `iconv.h` problems?*
- \* *Why don't other recipes find the files provided by my `*-native` recipe?*
- \* *Can I get rid of build output so I can start over?*
- \* *Why isn't there a way to append bbclass files like `bbappend` for recipes?*
- \* *How do I integrate a third-party vulnerability scanning tool?*

– *Customizing generated images*

- \* *What does the OpenEmbedded build system produce as output?*
- \* *How do I make the Yocto Project support my board?*
- \* *How do I make the Yocto Project support my package?*
- \* *What do I need to ship for license compliance?*
- \* *Do I have to make a full reflash after recompiling one package?*
- \* *How to prevent my package from being marked as machine specific?*
- \* *What's the difference between `target` and `target-native`?*
- \* *Why do `${bindir}` and `${libdir}` have strange values for `-native` recipes?*
- \* *How do I create images with more free space?*
- \* *Why aren't spaces in path names supported?*
- \* *I'm adding a binary in a recipe. Why is it different in the image?*

– *Issues on the running system*

- \* *How do I disable the cursor on my touchscreen device?*
- \* *How to always bring up connected network interfaces?*

### 6.16.1 General questions

#### How does Poky differ from OpenEmbedded?

The term *Poky* refers to the reference distribution that the Yocto Project provides, and a reference test configuration.

The *Poky* distribution is built using the *OpenEmbedded Build System* and *BitBake*. The *metadata* involved to build the *Poky* reference distribution is:

- *OpenEmbedded-Core (OE-Core)*, which is hosted at <https://git.openembedded.org/openembedded-core>.
- *meta-poky*, which defines the *poky* distro configuration file (*DISTRO*).

#### Nota

Poky also used to be a repository containing the combination of *BitBake*, *OpenEmbedded-Core (OE-Core)*, the *meta-yocto* repository and the Yocto Project documentation -- which were combined with the *combo-layer* tool.

This repository is still hosted at <https://git.yoctoproject.org/poky> and is still updated for maintained releases that are older than Whinlatter (5.3). Newer releases now use *bitbake-setup* to clone and setup the initial *OpenEmbedded Build System* environment. For more information on how to use *bitbake-setup*, see the *Build Rapida di un'Immagine con lo Yocto Project* document. An alternative can be to setup the above repositories manually, by following the *Setting Up the Poky Reference Distro Manually* section of the Yocto Project Development Tasks Manual.

#### How can you claim Poky / OpenEmbedded-Core is stable?

There are three areas that help with stability;

- The Yocto Project team keeps *OpenEmbedded-Core (OE-Core)* small and focused, containing around a thousand recipes as opposed to the thousands available in other OpenEmbedded community layers. Keeping it small makes it easy to test and maintain.
- The Yocto Project team runs manual and automated tests using a small, fixed set of reference hardware as well as emulated targets.
- The Yocto Project uses an *autobuilder*, which provides continuous build and integration tests.

#### Are there any products built using the OpenEmbedded build system?

See *Products that use the Yocto Project* in the Yocto Project Wiki. Don't hesitate to contribute to this page if you know other such products.



## Why isn't systemd the default init system in the Poky distro?

`systemd` is a desktop Linux init system with a specific focus that is not entirely aligned with a customisable "embedded" build system/environment.

It understandably mandates certain layouts and configurations which may or may not align with what the objectives and direction *OpenEmbedded-Core (OE-Core)* or Yocto Project want to take. It doesn't support all of our targets. For example `musl` support in `systemd` is problematic.

If it were our default, we would have to align with all their choices and this doesn't make sense. It is therefore a configuration option and available to anyone where the design goals align. But we are clear it is not the only way to handle init.

Our automated testing includes it through the `poky-altcfg DISTRO` and we don't really need it to be the default: it is tested, it works, and people can choose to use it.

## 6.16.2 Building environment

### Missing dependencies on the development system?

If your development system does not meet the required Git, tar, and Python versions, you can get the required tools on your host development system in different ways (i.e. building a tarball or downloading a tarball). See the "*Versioni richieste di Git, tar, Python, make e gcc*" section for steps on how to update your build tools.

### How does OpenEmbedded fetch source code? Will it work through a firewall or proxy server?

The way the build system obtains source code is highly configurable. You can setup the build system to get source code in most environments if HTTP transport is available.

When the build system searches for source code, it first tries the local download directory (`DL_DIR`). If that location fails, the *OpenEmbedded Build System* tries `PREMIRRORS`, the upstream source (specified in `SRC_URI`), and then `MIRRORS` in that order.

Assuming your distribution is "poky", the OpenEmbedded build system uses the Yocto Project source `PREMIRRORS` by default for SCM-based sources, upstreams for normal tarballs, and then falls back to a number of other mirrors including the Yocto Project source mirror if those fail.

As an example, you could add a specific server for the build system to attempt before any others by adding something like the following to a *configuration file*:

```
PREMIRRORS:prepend = "\
    git://.*/* https://downloads.yoctoproject.org/mirror/sources/ \
    ftp://.*/* https://downloads.yoctoproject.org/mirror/sources/ \
    http://.*/* https://downloads.yoctoproject.org/mirror/sources/ \
    https://.*/* https://downloads.yoctoproject.org/mirror/sources/ \
"
```

These changes cause the build system to intercept Git, FTP, HTTP, and HTTPS requests and direct them to the `http://` sources mirror. You can use `file://` URLs to point to local directories or network shares as well.

Another option is to set:

```
BB_NO_NETWORK = "1"
```

This statement tells BitBake to issue an error instead of trying to access the Internet. This technique is useful if you want to ensure code builds only from local sources.

Here is another technique:

```
BB_FETCH_PREMIRRORONLY = "1"
```

This statement limits the build system to pulling source from the *PREMIRRORS* only. Again, this technique is useful for reproducing builds.

Here is yet another technique:

```
BB_GENERATE_MIRROR_TARBALLS = "1"
```

This statement tells the build system to generate mirror tarballs. This technique is useful if you want to create a mirror server. If not, however, the technique can simply waste time during the build.

Finally, consider an example where you are behind an HTTP-only firewall. You could make the following changes to a *configuration file* as long as the *PREMIRRORS* server is current:

```
PREMIRRORS:prepend = "\n\ngit://.*.* https://downloads.yoctoproject.org/mirror/sources/ \n\nftp://.*.* https://downloads.yoctoproject.org/mirror/sources/ \n\nhttp://.*.* https://downloads.yoctoproject.org/mirror/sources/ \n\nhttps://.*.* https://downloads.yoctoproject.org/mirror/sources/ \n\n"\nBB_FETCH_PREMIRRORONLY = "1"
```

These changes would cause the build system to successfully fetch source over HTTP and any network accesses to anything other than the *PREMIRRORS* would fail.

Most source fetching by the OpenEmbedded build system is done by `wget` and you therefore need to specify the proxy settings in a `.wgetrc` file, which can be in your home directory if you are a single user or can be in `/usr/local/etc/wgetrc` as a global user file.

Here is the applicable code for setting various proxy types in the `.wgetrc` file. By default, these settings are disabled with comments. To use them, remove the comments:

```
# You can set the default proxies for Wget to use for http, https, and ftp.
# They will override the value in the environment.
#https_proxy = http://proxy.yoyodyne.com:18023/
#http_proxy = http://proxy.yoyodyne.com:18023/
#ftp_proxy = http://proxy.yoyodyne.com:18023/

# If you do not want to use proxy at all, set this to off.
#use_proxy = on
```

The build system also accepts `http_proxy`, `ftp_proxy`, `https_proxy`, and `all_proxy` set as to standard shell environment variables to redirect requests through proxy servers.

The Yocto Project also includes a `meta/conf/templates/default/site.conf.sample` file that shows how to configure a Git proxy server if needed.

**Nota**

You can find more information on the "[Working Behind a Network Proxy](#)" Wiki page.

### 6.16.3 Using the OpenEmbedded Build system

#### How do I use an external toolchain?

See the "*Optionally Using an External Toolchain*" section in the Development Task manual.

#### Why do I get chmod permission issues?

If you see the error `chmod: XXXXX new permissions are r-xrwxrwx, not r-xr-xr-x`, you are probably running the build on an NTFS filesystem. Instead, run the build system on a partition with a modern Linux filesystem such as `ext4`, `btrfs` or `xfs`.

#### I see many 404 errors trying to download sources. Is anything wrong?

Nothing is wrong. The OpenEmbedded build system checks any configured source mirrors before downloading from the upstream sources. The build system does this searching for both source archives and pre-checked out versions of SCM-managed software. These checks help in large installations because it can reduce load on the SCM servers themselves. This can also allow builds to continue to work if an upstream source disappears.

#### Why do I get random build failures?

If the same build is failing in totally different and random ways, the most likely explanation is:

- The hardware you are running the build on has some problem.
- You are running the build under virtualization, in which case the virtualization probably has bugs.

The OpenEmbedded build system processes a massive amount of data that causes lots of network, disk and CPU activity and is sensitive to even single-bit failures in any of these areas. True random failures have always been traced back to hardware or virtualization issues.

#### Why does the build fail with `iconv.h` problems?

When you try to build a native recipe, you may get an error message that indicates that GNU `libiconv` is not in use but `iconv.h` has been included from `libiconv`:

```
#error GNU libiconv not in use but included iconv.h is from libiconv
```

When this happens, you need to check whether you have a previously installed version of the header file in `/usr/local/include/`. If that's the case, you should either uninstall it or temporarily rename it and try the build again.

This issue is just a single manifestation of "system leakage" issues caused when the OpenEmbedded build system finds and uses previously installed files during a native build. This type of issue might not be limited to `iconv.h`. Make sure that leakage cannot occur from `/usr/local/include` and `/opt` locations.

### Why don't other recipes find the files provided by my `*-native` recipe?

Files provided by your native recipe could be missing from the native sysroot, your recipe could also be installing to the wrong place, or you could be getting permission errors during the `do_install` task in your recipe.

This situation happens when the build system used by a package does not recognize the environment variables supplied to it by *BitBake*. The incident that prompted this FAQ entry involved a Makefile that used an environment variable named `BINDIR` instead of the more standard variable `bindir`. The makefile's hardcoded default value of `"/usr/bin"` worked most of the time, but not for the recipe's `-native` variant. For another example, permission errors might be caused by a Makefile that ignores `DESTDIR` or uses a different name for that environment variable. Check the build system of the package to see if these kinds of issues exist.

### Can I get rid of build output so I can start over?

Yes --- you can easily do this. When you use BitBake to build an image, all the build output goes into the directory created when you run the build environment setup script (i.e. *oe-init-build-env*). By default, this *Build Directory* is named `build` but can be named anything you want.

Within the *Build Directory*, is the `tmp` directory. To remove all the build output yet preserve any source code or downloaded files from previous builds, simply remove the `tmp` directory.

### Why isn't there a way to append bbclass files like `bbappend` for recipes?

The Yocto Project has consciously chosen not to implement such functionality. Class code is designed to be shared and reused, and exposes some level of configuration to its users. We want to encourage people to share these changes so we can build the best classes.

If the `append` functionality was available for classes, our evidence and experience suggest that people would create their custom changes in their layer instead of sharing and discussing the issues and/or limitations they encountered. This would lead to bizarre class interactions when new layers are included. We therefore consciously choose to have a natural pressure to share class code improvements or fixes.

There are also technical considerations like which recipes a class append would apply to and how that would fit within the layer model. These are complications we think we can live without!

### How do I integrate a third-party vulnerability scanning tool?

The *OpenEmbedded Build System* produces SPDX files that contain the Software Bill Of Materials (SBOM) for any recipe that is built. For this it uses the *create-spdx* class. This class also creates a final SPDX document for an image recipe, found in the deployment directory (*DEPLOY\_DIR\_IMAGE*). See the *Creating a Software Bill of Materials* section of the Yocto Project Development Tasks Manual for more information of SBOMs generated by the *OpenEmbedded Build System*.

Some third-party vulnerability scanning tools have existing integration with the SPDX documents generated by the *OpenEmbedded Build System*. One example is *Blackduck*, which offers the `bd_scan_yocto_via_sbom` utility to scan the vulnerabilities using the SPDX document as input.

These third-party tools have the responsibility of providing support for integrating with the Yocto Project SBOMs.

Also see the *Verifica delle Vulnerabilità* section of the Yocto Project Development Tasks Manual for more information on dealing with vulnerabilities.

## 6.16.4 Customizing generated images

### What does the OpenEmbedded build system produce as output?

Because you can use the same set of recipes to create output of various formats, the output of an OpenEmbedded build depends on how you start it. Usually, the output is a flashable image ready for the target device.

### How do I make the Yocto Project support my board?

Support for an additional board is added by creating a Board Support Package (BSP) layer for it. For more information on how to create a BSP layer, see the *"Comprendere e Creare i Layer"* section in the Yocto Project Development Tasks Manual and the *Manuale del Board Support Package (BSP) di Yocto Project*.

Usually, if the board is not completely exotic, adding support in the Yocto Project is fairly straightforward.

### How do I make the Yocto Project support my package?

To add a package, you need to create a BitBake recipe. For information on how to create a BitBake recipe, see the *"Scrivere una Nuova Ricetta"* section in the Yocto Project Development Tasks Manual.

### What do I need to ship for license compliance?

This is a difficult question and you need to consult your lawyer for the answer for your specific case. It is worth bearing in mind that for GPL compliance, there needs to be enough information shipped to allow someone else to rebuild and produce the same end result you are shipping. This means sharing the source code, any patches applied to it, and also any configuration information about how that package was configured and built.

You can find more information on licensing in the *"Licenze"* section in the Yocto Project Overview and Concepts Manual and also in the *"Maintaining Open Source License Compliance During Your Product's Lifecycle"* section in the Yocto Project Development Tasks Manual.

### Do I have to make a full reflash after recompiling one package?

The OpenEmbedded build system can build packages in various formats such as IPK for OPKG, Debian package (.deb), or RPM. You can then upgrade only the modified packages using the package tools on the device, much like on a desktop distribution such as Ubuntu or Fedora. However, package management on the target is entirely optional.

### How to prevent my package from being marked as machine specific?

If you have machine-specific data in a package for one machine only but the package is being marked as machine-specific in all cases, you can set `SRC_URI_OVERRIDES_PACKAGE_ARCH = "0"` in the .bb file. However, but make sure the package is manually marked as machine-specific for the case that needs it. The code that handles `SRC_URI_OVERRIDES_PACKAGE_ARCH` is in the `meta/classes-global/base.bbclass` file.

### What's the difference between `target` and `target-native`?

The `*-native` targets are designed to run on the system being used for the build. These are usually tools that are needed to assist the build in some way such as `quilt-native`, which is used to apply patches. The non-native version is the one that runs on the target device.

### Why do `${bindir}` and `${libdir}` have strange values for `-native` recipes?

Executables and libraries might need to be used from a directory other than the directory into which they were initially installed. Complicating this situation is the fact that sometimes these executables and libraries are compiled with the expectation of being run from that initial installation target directory. If this is the case, moving them causes problems.

This scenario is a fundamental problem for package maintainers of mainstream Linux distributions as well as for the OpenEmbedded build system. As such, a well-established solution exists. Makefiles, Autotools configuration scripts, and other build systems are expected to respect environment variables such as `bindir`, `libdir`, and `sysconfdir` that indicate where executables, libraries, and data reside when a program is actually run. They are also expected to respect a `DESTDIR` environment variable, which is prepended to all the other variables when the build system actually installs the files. It is understood that the program does not actually run from within `DESTDIR`.

When the OpenEmbedded build system uses a recipe to build a target-architecture program (i.e. one that is intended for inclusion on the image being built), that program eventually runs from the root file system of that image. Thus, the build system provides a value of `"/usr/bin"` for `bindir`, a value of `"/usr/lib"` for `libdir`, and so forth.

Meanwhile, `DESTDIR` is a path within the *Build Directory*. However, when the recipe builds a native program (i.e. one that is intended to run on the build machine), that program is never installed directly to the build machine's root file system. Consequently, the build system uses paths within the Build Directory for `DESTDIR`, `bindir` and related variables. To better understand this, consider the following two paths (artificially broken across lines for readability) where the first is relatively normal and the second is not:

```
/home/maxtothemax/poky-bootchart2/build/tmp/work/i586-poky-linux/zlib/
1.2.8-r0/sysroot-destdir/usr/bin

/home/maxtothemax/poky-bootchart2/build/tmp/work/x86_64-linux/
zlib-native/1.2.8-r0/sysroot-destdir/home/maxtothemax/poky-bootchart2/
build/tmp/sysroots/x86_64-linux/usr/bin
```

Even if the paths look unusual, they both are correct --- the first for a target and the second for a native recipe. These paths are a consequence of the `DESTDIR` mechanism and while they appear strange, they are correct and in practice very effective.

### How do I create images with more free space?

By default, the OpenEmbedded build system creates images that are 1.3 times the size of the populated root filesystem. To affect the image size, you need to set various configurations:

- *Image Size:* The OpenEmbedded build system uses the `IMAGE_ROOTFS_SIZE` variable to define the size of the image in Kbytes. The build system determines the size by taking into account the initial root filesystem size before any modifications such as requested size for the image and any requested additional free disk space to be added to the image.

- *Overhead*: Use the `IMAGE_OVERHEAD_FACTOR` variable to define the multiplier that the build system applies to the initial image size, which is 1.3 by default.
- *Additional Free Space*: Use the `IMAGE_ROOTFS_EXTRA_SPACE` variable to add additional free space to the image. The build system adds this space to the image after it determines its `IMAGE_ROOTFS_SIZE`.

### Why aren't spaces in path names supported?

The Yocto Project team has tried to do this before but too many of the tools the OpenEmbedded build system depends on, such as `autoconf`, break when they find spaces in pathnames. Until that situation changes, the team will not support spaces in pathnames.

### I'm adding a binary in a recipe. Why is it different in the image?

The first most obvious change is the system stripping debug symbols from it. Setting `INHIBIT_PACKAGE_STRIP` to stop debug symbols being stripped and/or `INHIBIT_PACKAGE_DEBUG_SPLIT` to stop debug symbols being split into a separate file will ensure the binary is unchanged.

## 6.16.5 Issues on the running system

### How do I disable the cursor on my touchscreen device?

You need to create a form factor file as described in the "*File di Ricette Specifici per BSP*" section in the Yocto Project Board Support Packages (BSP) Developer's Guide. Set the `HAVE_TOUCHSCREEN` variable equal to one as follows:

```
HAVE_TOUCHSCREEN=1
```

### How to always bring up connected network interfaces?

The default interfaces file provided by the netbase recipe does not automatically bring up network interfaces. Therefore, you will need to add a BSP-specific netbase that includes an interfaces file. See the "*File di Ricette Specifici per BSP*" section in the Yocto Project Board Support Packages (BSP) Developer's Guide for information on creating these types of miscellaneous recipe files.

For example, add the following files to your layer:

```
meta-MACHINE/recipes-bsp/netbase/netbase/MACHINE/interfaces
meta-MACHINE/recipes-bsp/netbase/netbase_5.0.bbappend
```

## 6.17 Contributions and Additional Information

### 6.17.1 Introduzione

The Yocto Project team is happy for people to experiment with the Yocto Project. There is a number of places where you can find help if you run into difficulties or find bugs. This presents information about contributing and participating in the Yocto Project.

## 6.17.2 Contributions

The Yocto Project gladly accepts contributions. You can submit changes to the project either by creating and sending pull requests, or by submitting patches through email. For information on how to do both as well as information on how to identify the maintainer for each area of code, see the *Guida per i Collaboratori di Yocto Project e di OpenEmbedded*.

## 6.17.3 Yocto Project Bugzilla

The Yocto Project uses its own implementation of [Bugzilla](#) to track defects (bugs). Implementations of Bugzilla work well for group development because they track bugs and code changes, can be used to communicate changes and problems with developers, can be used to submit and review patches, and can be used to manage quality assurance.

Sometimes it is helpful to submit, investigate, or track a bug against the Yocto Project itself (e.g. when discovering an issue with some component of the build system that acts contrary to the documentation or your expectations).

For a general procedure and guidelines on how to use Bugzilla to submit a bug against the Yocto Project, see the following:

- The "*Segnalazione di un Difetto in Yocto Project e in OpenEmbedded*" section in the Yocto Project and OpenEmbedded Contributor Guide.
- The Yocto Project [Bugzilla](#) wiki page

For information on Bugzilla in general, see <https://www.bugzilla.org/about/>.

## 6.17.4 Mailing lists

There are multiple mailing lists maintained by the Yocto Project as well as related OpenEmbedded mailing lists for discussion, patch submission and announcements. To subscribe to one of the following mailing lists, click on the appropriate URL in the following list and follow the instructions:

- <https://lists.yoctoproject.org/g/yocto> --- general Yocto Project discussion mailing list.
- <https://lists.yoctoproject.org/g/yocto-patches> --- patch contribution mailing list for Yocto Project-related layers which do not have their own mailing list.
- <https://lists.openembedded.org/g/openembedded-core> --- discussion mailing list about OpenEmbedded-Core (the core metadata).
- <https://lists.openembedded.org/g/openembedded-devel> --- discussion mailing list about OpenEmbedded.
- <https://lists.openembedded.org/g/bitbake-devel> --- discussion mailing list about the *BitBake* build tool.
- <https://lists.yoctoproject.org/g/poky> --- discussion mailing list about *Poky*.
- <https://lists.yoctoproject.org/g/yocto-announce> --- mailing list to receive official Yocto Project release and milestone announcements.
- <https://lists.yoctoproject.org/g/docs> --- discussion mailing list about the Yocto Project documentation.

See also the [description of all mailing lists](#).



### 6.17.5 Internet Relay Chat (IRC)

Two IRC channels on [Libera Chat](#) are available for the Yocto Project and OpenEmbedded discussions:

- [#yocto](#)
- [#oe](#)

### 6.17.6 Links and Related Documentation

Here is a list of resources you might find helpful:

- [The Yocto Project Website](#): The home site for the Yocto Project.
- [The Yocto Project Main Wiki Page](#): The main wiki page for the Yocto Project. This page contains information about project planning, release engineering, QA & automation, a reference site map, and other resources related to the Yocto Project.
- [OpenEmbedded](#): The build system used by the Yocto Project. This project is the upstream, generic, embedded distribution from which the Yocto Project derives its build system (Poky) and to which it contributes.
- [BitBake](#): The tool used to process metadata.
- [BitBake User Manual](#): A comprehensive guide to the BitBake tool. If you want information on BitBake, see this manual.
- [Build Rapida di un'Immagine con lo Yocto Project](#): This short document lets you experience building an image using the Yocto Project without having to understand any concepts or details.
- [Manuale Introduttivo e Concetti di Yocto Project](#): This manual provides overview and conceptual information about the Yocto Project.
- [Manuale di Sviluppo dei Task di Yocto Project](#): This manual is a "how-to" guide that presents procedures useful to both application and system developers who use the Yocto Project.
- [Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit \(SDK/eSDK\) manual](#): This guide provides information that lets you get going with the standard or extensible SDK. An SDK, with its cross-development toolchains, allows you to develop projects inside or outside of the Yocto Project environment.
- [Manuale del Board Support Package \(BSP\) di Yocto Project](#): This guide defines the structure for BSP components. Having a commonly understood structure encourages standardization.
- [Manuale di Sviluppo del Kernel Linux di Yocto Project](#): This manual describes how to work with Linux Yocto kernels as well as provides a bit of conceptual information on the construction of the Yocto Linux kernel tree.
- [Yocto Project Reference Manual](#): This manual provides reference material such as variable, task, and class descriptions.
- [Yocto Project Mega-Manual](#): This manual is simply a single HTML file comprised of the bulk of the Yocto Project manuals. It makes it easy to search for phrases and terms used in the Yocto Project documentation set.
- [Manuale di Profilazione e Tracing di Yocto Project](#): This manual presents a set of common and generally useful tracing and profiling schemes along with their applications (as appropriate) to each tool.

- *Manuale Utente di Toaster*: This manual introduces and describes how to set up and use Toaster. Toaster is an Application Programming Interface (API) and web-based interface to the *OpenEmbedded Build System*, which uses BitBake, that reports build information.
  - *Yocto Project BitBake extension for VSCode*: This extension provides a rich feature set when working with BitBake recipes within the Visual Studio Code IDE.
  - *FAQ*: A list of commonly asked questions and their answers.
  - *Release Information*: Migration guides, release notes, new features, updates and known issues for the current and past releases of the Yocto Project.
  - *Bugzilla*: The bug tracking application the Yocto Project uses. If you find problems with the Yocto Project, you should report them using this application.
  - *Bugzilla Configuration and Bug Tracking Wiki Page*: Information on how to get set up and use the Yocto Project implementation of Bugzilla for logging and tracking Yocto Project defects.
  - Internet Relay Chat (IRC): Two IRC channels on *Libera Chat* are available for Yocto Project and OpenEmbedded discussions: #yocto and #oe, respectively.
  - *Quick EMUlator (QEMU)*: An open-source machine emulator and virtualizer.
- 

The Yocto Project ®

<docs@lists.yoctoproject.org>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza *Creative Commons Attribution-Share Alike 2.0 UK: England & Wales* pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo `docs@lists.yoctoproject.org` o di accedere su *Libera Chat* al canale #yocto.

---

## Manuale del Board Support Package (BSP) di Yocto Project

---

### 7.1 Manuale del Board Support Package (BSP) di Yocto Project

Un Board Support Package (BSP) è una raccolta di informazioni che definisce come supportare un particolare dispositivo hardware, un insieme di dispositivi o una piattaforma hardware. Il BSP include informazioni sulle funzionalità hardware presenti sul dispositivo, su eventuali bootloader essenziali, sulla configurazione del kernel e del device tree, nonché su tutti i driver hardware aggiuntivi necessari. Il BSP elenca anche tutti i componenti software aggiuntivi richiesti, oltre a uno stack software Linux generico per le funzionalità essenziali e opzionali della piattaforma.

Questa guida presenta informazioni sui layer BSP, definisce una struttura per i componenti in modo che i BSP seguano un layout comunemente compreso, illustra come personalizzare una ricetta per un BSP, affronta le licenze BSP e fornisce informazioni su come creare un layer BSP utilizzando il tool *bitbake-layers*.

#### 7.1.1 Layer BSP

Un BSP è costituito da una struttura di file all'interno di una directory di base. Nel loro insieme, la directory base, la sua struttura di file e il suo contenuto possono essere considerati come un layer BSP. Sebbene non sia un requisito rigoroso, i layer BSP in Yocto Project utilizzano la seguente convenzione di denominazione consolidata:

`meta-bsp_root_name`

La stringa "meta-" viene anteposta al nome della macchina o della piattaforma, che nella forma sopra riportata è "bsp\_root\_name".

**i Nota**

Poiché la convenzione di denominazione dei layer BSP è ben consolidata, è consigliabile seguirla durante la creazione dei layer. Tecnicamente parlando, il nome di un layer BSP non deve necessariamente iniziare con `meta-`. Tuttavia, diversi script e strumenti nell'ambiente di sviluppo di Yocto Project presuppongono questa convenzione.

Per comprendere meglio il concetto di layer BSP, si considerino i BSP supportati e forniti da Yocto Project in ogni release. È possibile visualizzare i layer nei repository sorgente di Yocto Project (vedere *I Repository del Codice Sorgente di Yocto Project*) tramite un'interfaccia web all'indirizzo <https://git.yoctoproject.org/>. Accedendo a quell'interfaccia, si troverà un elenco di repository sotto la voce "Yocto Metadata Layers".

**i Nota**

I layer non più attivamente supportati da Yocto Project compaiono sotto la voce "Yocto Metadata Layer Archive."

Ogni repository corrisponde a un layer BSP supportato da Yocto Project (ad esempio, `meta-raspberrypi` e `meta-intel`). Ciascuno di questi layer è un repository a sé stante e cliccando sul nome del layer vengono visualizzati due URL da cui è possibile clonare il repository del layer sul proprio sistema locale. Ecco un esempio che clona il layer BSP Raspberry Pi:

```
$ git clone https://git.yoctoproject.org/meta-raspberrypi
```

Oltre ai layer BSP, il layer `meta-yocto-bsp` fa parte di `meta-yocto`. Il layer `meta-yocto-bsp` gestisce diversi BSP di riferimento, tra cui il Beaglebone basato su ARM e versioni generiche di macchine IA a 32 e 64 bit.

Per informazioni sul tipico flusso di lavoro di sviluppo BSP, consultare la sezione *Sviluppo di un Board Support Package (BSP)*. Per ulteriori informazioni su come configurare una copia locale dei file sorgente da un repository Git, consultare la sezione *Setting Up the Poky Reference Distro Manually* nel Manuale di Sviluppo dei Task di Yocto Project.

La directory base del layer BSP (`meta-bsp_root_name`) è la directory radice di quel layer. Questa directory è quella che si aggiunge alla variabile `BBLAYERS` nel file `build/conf/bblayers.conf` che si trova nella *Build Directory*, che viene creata dopo aver eseguito lo script di configurazione dell'ambiente di build di OpenEmbedded (ovvero `oe-init-build-env`). L'aggiunta della directory radice consente a *OpenEmbedded Build System* di riconoscere il layer BSP e da esso di creare un'immagine. Ecco un esempio:

```
BBLAYERS ?= " \
    /usr/local/src/yocto/meta \
    /usr/local/src/yocto/meta-poky \
    /usr/local/src/yocto/meta-yocto-bsp \
    /usr/local/src/yocto/meta-mylayer \
    "
```

**i Nota**

L'ordine e il `BFILE_PRIORITY` per i layer elencati in `BBLAYERS` sono importanti. Ad esempio, se più layer definiscono una configurazione macchina, il sistema di build OpenEmbedded utilizza l'ultimo layer cercato, a parità di priorità. Il sistema di build procede dall'alto verso il basso, attraverso i layer elencati in `BBLAYERS`.

Alcuni BSP richiedono o dipendono da layer aggiuntivi oltre al layer radice del BSP per essere funzionanti. In questo caso, è necessario specificare questi layer nella sezione "Dependencies" del layer radice del BSP nel file `README`. Inoltre, se esistono istruzioni di compilazione per il BSP, è necessario aggiungerle alla sezione "Dependencies".

Alcuni layer fungono da layer per contenere altri layer del BSP. Questi layer sono noti come "*container layers*". Un esempio di questo tipo di layer è il layer `meta-openembedded` di OpenEmbedded. Il layer `meta-openembedded` contiene molti layer `meta-*`. In casi come questo, è necessario includere i nomi dei layer effettivi con cui si desidera lavorare, ad esempio:

```
BBLAYERS ?= " \
    /usr/local/src/yocto/meta \
    /usr/local/src/yocto/meta-poky \
    /usr/local/src/yocto/meta-yocto-bsp \
    /usr/local/src/yocto/meta-mylayer \
    ../meta-openembedded/meta-oe \
    ../meta-openembedded/meta-perl \
    ../meta-openembedded/meta-networking \
"
```

e così via.

Per ulteriori informazioni sui layer, consultare la sezione "*Comprendere e Creare i Layer*" del Manuale di Sviluppo dei Task di Yocto Project.

## 7.1.2 Preparazione dell'Host di Build per Lavorare con i Layer BSP

Questa sezione descrive come preparare l'host di build per lavorare con i layer BSP. Una volta configurato l'host, è possibile creare il layer come descritto nella sezione "*Creazione di un Nuovo Layer BSP Tramite lo Script `bitbake-layers`*".

**i Nota**

Per informazioni sulla struttura dei BSP, consultare la sezione *Esempio di Struttura del Filesystem*.

1. *Configurazione dell'Ambiente di Build:* Assicurarsi di aver configurato BitBake in una shell. Consultare la sezione "*Preparing the Build Host*" section nel Manuale di Sviluppo dei Task di Yocto Project per informazioni su come preparare un *build host*.
2. *Preparazione dei Repository Sorgente:*

Esistono due modi per configurare la distribuzione di riferimento *Poky*:

- Utilizzando l'utilità da riga di comando `bitbake-setup` di *BitBake*. Seguire le istruzioni riportate in:

## Setting Up The Environment With bitbake-setup

- Clonando manualmente i repository necessari. Seguire le istruzioni riportate in:

*Setting Up the Poky Reference Distro Manually*

3. *Individuazione del layer BSP Desiderato:* Yocto Project supporta numerosi BSP, gestiti in layer dedicati o in layer progettati per contenerne diversi. Il [Layer Index](#) può essere utile per trovare i layer BSP da utilizzare.
4. *Clonare Facoltativamente il Layer BSP meta-intel:* Se l'hardware si basa su CPU e dispositivi Intel attuali, si può utilizzare questo layer BSP. Per maggiori dettagli sul layer BSP `meta-intel`, consultare il file [README](#) del layer.
  1. *Accedere alla Directory dei Sorgenti:* In genere, il repository Git `meta-intel` viene posizionato accanto agli altri layer della build.
  2. *Clonare il Layer:*

```
$ git clone https://git.yoctoproject.org/meta-intel.git
Cloning into 'meta-intel'...
remote: Counting objects: 15585, done.
remote: Compressing objects: 100% (5056/5056), done.
remote: Total 15585 (delta 9123), reused 15329 (delta 8867)
Receiving objects: 100% (15585/15585), 4.51 MiB | 3.19 MiB/s, done.
Resolving deltas: 100% (9123/9123), done.
Checking connectivity... done.
```

3. *Check Out del Branch Corretto:* Il branch che si sceglie per `meta-intel` deve corrispondere al branch utilizzato per la release di Yocto Project (ad esempio, `blacksail`):

```
$ cd meta-intel
$ git checkout -b blacksail remotes/origin/blacksail
Branch blacksail set up to track remote branch
blacksail from origin.
Switched to a new branch 'blacksail'
```

**i Nota**

Per visualizzare i nomi dei branch disponibili in un repository clonato, si usa il comando `git branch -a`.

5. *Configurazione Facoltativa di un Layer BSP Alternativo:* Se l'hardware può essere utilizzato più facilmente con un BSP esistente non incluso nel layer BSP `meta-intel`, si può clonare tale layer BSP.

La procedura è identica a quella utilizzata per il layer `meta-intel` ad eccezione del nome del layer. Ad esempio, se si determina che l'hardware è più simile al layer `meta-raspberrypi`, clonare quel layer:

```
$ git clone https://git.yoctoproject.org/meta-raspberrypi
Cloning into 'meta-raspberrypi'...
```

(continues on next page)

(continua dalla pagina precedente)

```
remote: Counting objects: 4743, done.
remote: Compressing objects: 100% (2185/2185), done.
remote: Total 4743 (delta 2447), reused 4496 (delta 2258)
Receiving objects: 100% (4743/4743), 1.18 MiB | 0 bytes/s, done.
Resolving deltas: 100% (2447/2447), done.
Checking connectivity... done.
```

6. *Inizializzazione dell'Ambiente di Build*: Mentre ci si trova nella directory *Source Directory*, eseguire lo script di configurazione dell'ambiente *oe-init-build-env* che si trova in *OpenEmbedded-Core (OE-Core)* per definire l'ambiente di build OpenEmbedded sul proprio host di build.

```
$ source layers/openembedded-core/oe-init-build-env
```

Tra le altre cose, lo script crea la *Build Directory*, che è "build". Dopo l'esecuzione dello script, la directory di lavoro corrente verrà impostata su *Build Directory*.

#### Nota

In alternativa, è possibile caricare il file *init-build-env* fornito da *bitbake-setup*

### 7.1.3 Esempio di Struttura del Filesystem

Definire una struttura di directory BSP comune consente agli utenti finali di comprendere e familiarizzare con tale standard. Un formato comune incoraggia inoltre la standardizzazione del supporto software per l'hardware.

La struttura proposta descritta in questa sezione presenta elementi specifici del sistema di build OpenEmbedded. L'obiettivo è che gli sviluppatori possano utilizzare questa struttura con altri sistemi di build oltre a OpenEmbedded. È inoltre previsto che sia semplice estrarre informazioni e convertirle in altri formati, se necessario. Il sistema di build OpenEmbedded, tramite il suo meccanismo standard di *layer mechanism*, può accettare direttamente il formato descritto come layer. Il layer BSP raccoglie tutti i dettagli specifici dell'hardware in un unico punto utilizzando un formato standard, utile per chiunque desideri utilizzare la piattaforma hardware, indipendentemente dal sistema di build utilizzato.

La specifica BSP non include un sistema di build o altri strumenti: essa riguarda esclusivamente i componenti specifici dell'hardware. Al punto di distribuzione finale, è possibile distribuire il layer BSP combinato con un sistema di build e altri strumenti. È importante mantenere la distinzione tra layer BSP, sistema di build e tool come componenti separati che possono essere combinati in determinati prodotti finali.

Prima di esaminare la struttura di directory consigliata all'interno di un layer BSP, è bene sapere che esistono alcuni requisiti affinché un layer BSP sia considerato conforme a Yocto Project. Per l'elenco di tali requisiti, consultare la sezione "*Requisiti per i BSP Rilasciati*".

Di seguito è riportata la struttura di directory tipica per un layer BSP. Sebbene questa struttura di base rappresenti lo standard, è importante tenere presente che il layout effettivo dei singoli BSP potrebbe differire.

```
meta-bsp_root_name/
meta-bsp_root_name/bsp_license_file
```

(continues on next page)

(continua dalla pagina precedente)

```
meta-bsp_root_name/README
meta-bsp_root_name/README.sources
meta-bsp_root_name/binary/bootable_images
meta-bsp_root_name/conf/layer.conf
meta-bsp_root_name/conf/machine/*.conf
meta-bsp_root_name/recipes-bsp/*
meta-bsp_root_name/recipes-core/*
meta-bsp_root_name/recipes-graphics/*
meta-bsp_root_name/recipes-kernel/linux/linux-yocto_kernel_rev.bbappend
```

Di seguito è riportato un esempio del layer BSP per Raspberry Pi disponibile nei [Source Repositories](#):

```
meta-raspberrypi/COPYING.MIT
meta-raspberrypi/README.md
meta-raspberrypi/classes
meta-raspberrypi/classes/sdcard_image-rpi.bbclass
meta-raspberrypi/conf/
meta-raspberrypi/conf/layer.conf
meta-raspberrypi/conf/machine/
meta-raspberrypi/conf/machine/raspberrypi-cm.conf
meta-raspberrypi/conf/machine/raspberrypi-cm3.conf
meta-raspberrypi/conf/machine/raspberrypi.conf
meta-raspberrypi/conf/machine/raspberrypi0-wifi.conf
meta-raspberrypi/conf/machine/raspberrypi0.conf
meta-raspberrypi/conf/machine/raspberrypi2.conf
meta-raspberrypi/conf/machine/raspberrypi3-64.conf
meta-raspberrypi/conf/machine/raspberrypi3.conf
meta-raspberrypi/conf/machine/include
meta-raspberrypi/conf/machine/include/rpi-base.inc
meta-raspberrypi/conf/machine/include/rpi-default-providers.inc
meta-raspberrypi/conf/machine/include/rpi-default-settings.inc
meta-raspberrypi/conf/machine/include/rpi-default-versions.inc
meta-raspberrypi/conf/machine/include/tune-arm1176jzf-s.inc
meta-raspberrypi/docs
meta-raspberrypi/docs/Makefile
meta-raspberrypi/docs/conf.py
meta-raspberrypi/docs/contributing.md
meta-raspberrypi/docs/extra-apps.md
meta-raspberrypi/docs/extra-build-config.md
meta-raspberrypi/docs/index.rst
meta-raspberrypi/docs/layer-contents.md
meta-raspberrypi/docs/readme.md
meta-raspberrypi/files
```

(continues on next page)



(continua dalla pagina precedente)

```
meta-raspberrypi/files/custom-licenses
meta-raspberrypi/files/custom-licenses/Broadcom
meta-raspberrypi/recipes-bsp
meta-raspberrypi/recipes-bsp/bootfiles
meta-raspberrypi/recipes-bsp/bootfiles/bcm2835-bootfiles.bb
meta-raspberrypi/recipes-bsp/bootfiles/rpi-config_git.bb
meta-raspberrypi/recipes-bsp/common
meta-raspberrypi/recipes-bsp/common/firmware.inc
meta-raspberrypi/recipes-bsp/formfactor
meta-raspberrypi/recipes-bsp/formfactor/formfactor
meta-raspberrypi/recipes-bsp/formfactor/formfactor/raspberrypi
meta-raspberrypi/recipes-bsp/formfactor/formfactor/raspberrypi/machconfig
meta-raspberrypi/recipes-bsp/formfactor/formfactor_%.bbappend
meta-raspberrypi/recipes-bsp/rpi-u-boot-src
meta-raspberrypi/recipes-bsp/rpi-u-boot-src/files
meta-raspberrypi/recipes-bsp/rpi-u-boot-src/files/boot.cmd.in
meta-raspberrypi/recipes-bsp/rpi-u-boot-src/rpi-u-boot-scr.bb
meta-raspberrypi/recipes-bsp/u-boot
meta-raspberrypi/recipes-bsp/u-boot/u-boot
meta-raspberrypi/recipes-bsp/u-boot/u-boot/*.patch
meta-raspberrypi/recipes-bsp/u-boot/u-boot_%.bbappend
meta-raspberrypi/recipes-connectivity
meta-raspberrypi/recipes-connectivity/bluez5
meta-raspberrypi/recipes-connectivity/bluez5/bluez5
meta-raspberrypi/recipes-connectivity/bluez5/bluez5/*.patch
meta-raspberrypi/recipes-connectivity/bluez5/bluez5/BCM43430A1.hcd
meta-raspberrypi/recipes-connectivity/bluez5/bluez5/brcm43438.service
meta-raspberrypi/recipes-connectivity/bluez5/bluez5_%.bbappend
meta-raspberrypi/recipes-core
meta-raspberrypi/recipes-core/images
meta-raspberrypi/recipes-core/images/rpi-basic-image.bb
meta-raspberrypi/recipes-core/images/rpi-hwup-image.bb
meta-raspberrypi/recipes-core/images/rpi-test-image.bb
meta-raspberrypi/recipes-core/packagegroups
meta-raspberrypi/recipes-core/packagegroups/packagegroup-rpi-test.bb
meta-raspberrypi/recipes-core/psplash
meta-raspberrypi/recipes-core/psplash/files
meta-raspberrypi/recipes-core/psplash/files/psplash-raspberrypi-img.h
meta-raspberrypi/recipes-core/psplash/psplash_git.bbappend
meta-raspberrypi/recipes-core/udev
meta-raspberrypi/recipes-core/udev/udev-rules-rpi
meta-raspberrypi/recipes-core/udev/udev-rules-rpi/99-com.rules
meta-raspberrypi/recipes-core/udev/udev-rules-rpi.bb
```

(continues on next page)

(continua dalla pagina precedente)

```
meta-raspberrypi/recipes-devtools
meta-raspberrypi/recipes-devtools/bcm2835
meta-raspberrypi/recipes-devtools/bcm2835/bcm2835_1.52.bb
meta-raspberrypi/recipes-devtools/pi-blaster
meta-raspberrypi/recipes-devtools/pi-blaster/files
meta-raspberrypi/recipes-devtools/pi-blaster/files/*.patch
meta-raspberrypi/recipes-devtools/pi-blaster/pi-blaster_git.bb
meta-raspberrypi/recipes-devtools/python
meta-raspberrypi/recipes-devtools/python/python-rtimu
meta-raspberrypi/recipes-devtools/python/python-rtimu/*.patch
meta-raspberrypi/recipes-devtools/python/python-rtimu_git.bb
meta-raspberrypi/recipes-devtools/python/python-sense-hat_2.2.0.bb
meta-raspberrypi/recipes-devtools/python/rpi-gpio
meta-raspberrypi/recipes-devtools/python/rpi-gpio/*.patch
meta-raspberrypi/recipes-devtools/python/rpi-gpio_0.6.3.bb
meta-raspberrypi/recipes-devtools/python/rpio
meta-raspberrypi/recipes-devtools/python/rpio/*.patch
meta-raspberrypi/recipes-devtools/python/rpio_0.10.0.bb
meta-raspberrypi/recipes-devtools/wiringPi
meta-raspberrypi/recipes-devtools/wiringPi/files
meta-raspberrypi/recipes-devtools/wiringPi/files/*.patch
meta-raspberrypi/recipes-devtools/wiringPi/wiringpi_git.bb
meta-raspberrypi/recipes-graphics
meta-raspberrypi/recipes-graphics/eglinfo
meta-raspberrypi/recipes-graphics/eglinfo/eglinfo-fb_%.bbappend
meta-raspberrypi/recipes-graphics/eglinfo/eglinfo-x11_%.bbappend
meta-raspberrypi/recipes-graphics/mesa
meta-raspberrypi/recipes-graphics/mesa/mesa-gl_%.bbappend
meta-raspberrypi/recipes-graphics/mesa/mesa_%.bbappend
meta-raspberrypi/recipes-graphics/userland
meta-raspberrypi/recipes-graphics/userland/userland
meta-raspberrypi/recipes-graphics/userland/userland/*.patch
meta-raspberrypi/recipes-graphics/userland/userland_git.bb
meta-raspberrypi/recipes-graphics/vc-graphics
meta-raspberrypi/recipes-graphics/vc-graphics/files
meta-raspberrypi/recipes-graphics/vc-graphics/files/egl.pc
meta-raspberrypi/recipes-graphics/vc-graphics/files/vchiq.sh
meta-raspberrypi/recipes-graphics/vc-graphics/vc-graphics-hardfp.bb
meta-raspberrypi/recipes-graphics/vc-graphics/vc-graphics.bb
meta-raspberrypi/recipes-graphics/vc-graphics/vc-graphics.inc
meta-raspberrypi/recipes-graphics/wayland
meta-raspberrypi/recipes-graphics/wayland/wayland_%.bbappend
meta-raspberrypi/recipes-graphics/xorg-xserver
```

(continues on next page)

(continua dalla pagina precedente)

```

meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config/rpi
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config/rpi/xorg.conf
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config/rpi/xorg.conf.d
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config/rpi/xorg.conf.d/
↪10-evdev.conf
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config/rpi/xorg.conf.d/
↪98-pitft.conf
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config/rpi/xorg.conf.d/
↪99-calibration.conf
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xf86-config_0.1.bbappend
meta-raspberrypi/recipes-graphics/xorg-xserver/xserver-xorg_%.bbappend
meta-raspberrypi/recipes-kernel
meta-raspberrypi/recipes-kernel/linux-firmware
meta-raspberrypi/recipes-kernel/linux-firmware/files
meta-raspberrypi/recipes-kernel/linux-firmware/files/brcmfmac43430-sdio.bin
meta-raspberrypi/recipes-kernel/linux-firmware/files/brcmfmac43430-sdio.txt
meta-raspberrypi/recipes-kernel/linux-firmware/linux-firmware_%.bbappend
meta-raspberrypi/recipes-kernel/linux
meta-raspberrypi/recipes-kernel/linux/linux-raspberrypi-dev.bb
meta-raspberrypi/recipes-kernel/linux/linux-raspberrypi.inc
meta-raspberrypi/recipes-kernel/linux/linux-raspberrypi_4.14.bb
meta-raspberrypi/recipes-kernel/linux/linux-raspberrypi_4.9.bb
meta-raspberrypi/recipes-multimedia
meta-raspberrypi/recipes-multimedia/gstreamer
meta-raspberrypi/recipes-multimedia/gstreamer/gstreamer1.0-omx
meta-raspberrypi/recipes-multimedia/gstreamer/gstreamer1.0-omx/*.patch
meta-raspberrypi/recipes-multimedia/gstreamer/gstreamer1.0-omx_%.bbappend
meta-raspberrypi/recipes-multimedia/gstreamer/gstreamer1.0-plugins-bad_%.bbappend
meta-raspberrypi/recipes-multimedia/gstreamer/gstreamer1.0-omx-1.12
meta-raspberrypi/recipes-multimedia/gstreamer/gstreamer1.0-omx-1.12/*.patch
meta-raspberrypi/recipes-multimedia/omxplayer
meta-raspberrypi/recipes-multimedia/omxplayer/omxplayer
meta-raspberrypi/recipes-multimedia/omxplayer/omxplayer/*.patch
meta-raspberrypi/recipes-multimedia/omxplayer/omxplayer_git.bb
meta-raspberrypi/recipes-multimedia/x264
meta-raspberrypi/recipes-multimedia/x264/x264_git.bbappend
meta-raspberrypi/wic
meta-raspberrypi/wic/sdimage-raspberrypi.wks

```

Le sezioni seguenti descrivono ciascuna parte del formato BSP proposto.

## File di Licenza

È possibile trovare questi file nel layer BSP al seguente path:

```
meta-bsp_root_name/bsp_license_file
```

Questi file opzionali soddisfano i requisiti di licenza per il BSP. Il tipo o i tipi di file qui presenti possono variare a seconda dei requisiti di licenza. Ad esempio, nel BSP per Raspberry Pi, tutti i requisiti di licenza sono gestiti dal file `COPYING.MIT`.

I file di licenza possono essere MIT, BSD, GPLv\* e così via. Questi file sono consigliati per il BSP, ma sono opzionali e la loro gestione è a completa discrezione dello sviluppatore del BSP. Per informazioni su come mantenere la conformità delle licenze, consultare la sezione "*Maintaining Open Source License Compliance During Your Product's Lifecycle*" nel Manuale di Sviluppo dei Task di Yocto Project.

## File README

È possibile trovare questo file nel layer BSP al seguente path:

```
meta-bsp_root_name/README
```

Questo file fornisce informazioni su come avviare le immagini live che sono facoltativamente incluse nella directory `binary/`. Il file `README` fornisce anche le informazioni necessarie per la creazione dell'immagine.

Il file `README` deve contenere, come minimo, un elenco delle dipendenze, inclusi i nomi di eventuali altri layer da cui dipende il BSP e il nome del manutentore del BSP con i relativi recapiti.

## File README.sources

È possibile trovare questo file nel layer BSP al seguente path:

```
meta-bsp_root_name/README.sources
```

Questo file fornisce informazioni su dove trovare i file sorgente del BSP utilizzati per creare le immagini (se presenti) che si trovano nella directory `meta-bsp_root_name/binary`. Le immagini nella directory `binary` sono quelle rilasciate con il BSP. Le informazioni contenute nel file `README.sources` aiutano anche a trovare i *Metadata* utilizzati per generare le immagini fornite con il BSP.

### Nota

Se la directory `binary` del BSP non esiste o non contiene immagini, un file `README.sources` esistente è inutile e di solito non esiste.

## Binari Utente Precompilati

È possibile trovare questi file nel layer BSP al seguente path:

```
meta-bsp_root_name/binary/bootable_images
```

Questa area opzionale contiene kernel precompilati e immagini del filesystem utente rilasciate con il BSP, adatte al sistema target. Questa directory contiene in genere immagini grafiche (ad esempio Sato) e immagini live minimali, quando il tarball del BSP è stato creato e reso disponibile sul sito web [Yocto Project](#). È possibile utilizzare questi kernel e immagini per avviare un sistema e iniziare rapidamente le attività di sviluppo.

I tipi esatti di binari presenti dipendono fortemente dall'hardware. Il file [README](#) dovrebbe essere presente nel layer BSP e spiega come utilizzare le immagini con l'hardware target. Inoltre, il file [README.sources](#) dovrebbe essere presente per individuare i sorgenti utilizzati per la creazione delle immagini e fornire informazioni sui metadati.

## File di Configurazione del Layer

È possibile trovare questo file nel layer BSP al seguente path:

```
meta-bsp_root_name/conf/layer.conf
```

Il file `conf/layer.conf` identifica la struttura dei file come layer, ne specifica il contenuto e contiene informazioni su come il sistema di build deve utilizzarlo. In genere, un file boilerplate standard come il seguente funziona. Nell'esempio seguente, è necessario sostituire "bsp" con il nome effettivo del BSP (ad esempio, "bsp\_root\_name" dal modello dell'esempio).

```
# We have a conf and classes directory, add to BBPATH
BBPATH .= ":${LAYERDIR}"

# We have a recipes directory containing .bb and .bbappend files, add to BBFILES
BBFILES += "${LAYERDIR}/recipes-*/*/*.bb \
           ${LAYERDIR}/recipes-*/*/*.bbappend"

BBFILE_COLLECTIONS += "bsp"
BBFILE_PATTERN_bsp = "^${LAYERDIR}/"
BBFILE_PRIORITY_bsp = "6"
LAYERDEPENDS_bsp = "intel"
```

Per illustrare le sostituzioni di stringhe, ecco le corrispondenti istruzioni dal file `conf/layer.conf` del Raspberry Pi:

```
# We have a conf and classes directory, append to BBPATH
BBPATH .= ":${LAYERDIR}"

# We have a recipes directory containing .bb and .bbappend files, add to BBFILES
BBFILES += "${LAYERDIR}/recipes-*/*/*.bb \
           ${LAYERDIR}/recipes-*/*/*.bbappend"

BBFILE_COLLECTIONS += "raspberrypi"
BBFILE_PATTERN_raspberrypi := "^${LAYERDIR}/"
BBFILE_PRIORITY_raspberrypi = "9"

# Additional license directories.
```

(continues on next page)

(continua dalla pagina precedente)

```
LICENSE_PATH += "${LAYERDIR}/files/custom-licenses"  
.  
.  
.
```

Questo file si limita a far conoscere a *BitBake* le directory delle ricette e della configurazione. Il file deve esistere affinché il sistema di build OpenEmbedded possa riconoscere il BSP.

## Opzioni di Configurazione dell'Hardware

È possibile trovare questi file nel layer BSP al seguente path:

```
meta-bsp_root_name/conf/machine/*.conf
```

I file di configurazione della macchina raggruppano tutte le informazioni contenute altrove nel BSP in un formato comprensibile al sistema di build. Ogni layer BSP richiede almeno un file di configurazione della macchina. Se il BSP supporta più macchine, possono esistere più file di configurazione della macchina. Questi nomi di file corrispondono ai valori che gli utenti hanno impostato per la variabile *MACHINE*.

Questi file definiscono elementi come il pacchetto del kernel da utilizzare (*PREFERRED\_PROVIDER* di *virtual/kernel*), i driver hardware da includere nei diversi tipi di immagini, eventuali componenti software speciali necessari, informazioni sul bootloader e requisiti specifici per il formato dell'immagine.

Questo file di configurazione potrebbe includere anche un file di "tuning" hardware, comunemente utilizzato per definire l'architettura del pacchetto e specificare i flag di ottimizzazione, scelti con cura per ottenere le migliori prestazioni su un determinato processore.

I file di tuning si trovano nella directory `meta/conf/machine/include` all'interno di *OpenEmbedded-Core (OE-Core)*. Ad esempio, molti file `tune-*` (come `tune-arm1136jfs.inc`, `tune-1586-nlp.inc`, e così via) si trovano nella directory `meta/conf/machine/include`.

Per utilizzare un file include, è sufficiente includerlo nel file di configurazione della macchina. Ad esempio, il file `raspberrypi3.conf` del BSP del Raspberry Pi contiene la seguente istruzione:

```
include conf/machine/include/rpi-base.inc
```

## File di Ricette Specifici per BSP

È possibile trovare questi file nel layer BSP al seguente path:

```
meta-bsp_root_name/recipes-bsp/*
```

Questa directory opzionale contiene file di ricette specifici per il BSP. In particolare, si tratta dei file relativi al fattore di forma. Ad esempio, nel BSP per Raspberry Pi, è presente il file `formfactor_%.bbappend`, un file di append utilizzato per estendere la ricetta che avvia la compilazione. Inoltre, sono presenti impostazioni specifiche della macchina utilizzate durante la compilazione, definite dal file `machconfig` più in basso nella directory. Ecco il file `machconfig` per il BSP per Raspberry Pi:

```
HAVE_TOUCHSCREEN=0
HAVE_KEYBOARD=1

DISPLAY_CAN_ROTATE=0
DISPLAY_ORIENTATION=0
DISPLAY_DPI=133
```

### Nota

Se un BSP non ha una voce per il fattore di forma, vengono impostati i valori di default in base al file di configurazione del fattore di forma installato dalla ricetta principale del fattore di forma `meta/recipes-bsp/formfactor/formfactor_0.0.bb`, che si trova in *OpenEmbedded-Core (OE-Core)*.

## File di Supporto per il Display

È possibile trovare questi file nel layer BSP al seguente path:

```
meta-bsp_root_name/recipes-graphics/*
```

Questa directory opzionale contiene le ricette per il BSP qualora quest'ultimo abbia requisiti specifici per il supporto grafico. Tutti i file necessari al BSP per supportare un display sono conservati qui.

## Configurazione del Kernel Linux

È possibile trovare questi file nel layer BSP al seguente path:

```
meta-bsp_root_name/recipes-kernel/linux/linux*.bbappend
meta-bsp_root_name/recipes-kernel/linux/*.bb
```

I file di append (\*.bbappend) modificano la ricetta principale del kernel utilizzata per la creazione dell'immagine. I file \*.bb rappresentano una ricetta del kernel fornita dallo sviluppatore. Questa area della gerarchia del BSP può contenere entrambi i tipi di file, sebbene, in pratica, sia probabile che se ne trovi uno o l'altro.

Per il proprio BSP, in genere è consigliabile utilizzare una ricetta del kernel di Yocto Project esistente, reperibile in *OpenEmbedded-Core (OE-Core)* in `meta/recipes-kernel/linux`. È possibile aggiungere modifiche specifiche per la macchina alla ricetta del kernel utilizzando un file di append con un nome simile, che si trova nel layer BSP del dispositivo target (ad esempio, la directory `meta-bsp_root_name/recipes-kernel/linux`).

Supponiamo di utilizzare la ricetta `linux-yocto_6.12.bb` per compilare il kernel. In altre parole, abbiamo selezionato il kernel nel file `"bsp_root_name".conf` aggiungendo le istruzioni *PREFERRED\_PROVIDER* e *PREFERRED\_VERSION* come di seguito:

```
PREFERRED_PROVIDER_virtual/kernel ?= "linux-yocto"
PREFERRED_VERSION_linux-yocto ?= "6.12%"
```

**i Nota**

Quando il provider preferito è quello di default, l'istruzione *PREFERRED\_PROVIDER* non compare nel file `"bsp_root_name".conf`.

Il file `linux-yocto_6.12.bbappend` viene utilizzato per aggiungere impostazioni BSP specifiche al kernel, configurando così il kernel per il proprio BSP specifico.

Ulteriori informazioni sul contenuto del file di append sono disponibili nella sezione "*Creating the Append File*" del Manuale di Sviluppo del Kernel Linux di Yocto Project.

Un'alternativa è la creazione di una ricetta del kernel personalizzata per il BSP. Un buon esempio è il BSP per Raspberry Pi. Esaminando la directory `recipes-kernel/linux` in quel layer, si possono trovare le seguenti ricette specifiche per Raspberry Pi e i relativi file:

```
files/
linux-raspberrypi_6.12.bb
linux-raspberrypi_6.1.bb
linux-raspberrypi_6.6.bb
linux-raspberrypi-dev.bb
linux-raspberrypi.inc
linux-raspberrypi-v7_6.12.bb
linux-raspberrypi-v7_6.1.bb
linux-raspberrypi-v7_6.6.bb
linux-raspberrypi-v7.inc
```


## 7.1.4 Sviluppo di un Board Support Package (BSP)

Questa sezione descrive la procedura generale per la creazione di un BSP. Sebbene non sia obbligatorio per la creazione di un BSP, il repository `meta-intel`, che contiene molti BSP supportati da Yocto Project, è parte integrante dell'esempio.

Per un esempio che mostra come creare un nuovo layer utilizzando gli strumenti, consultare la sezione "*Creazione di un Nuovo Layer BSP Tramite lo Script `bitbake-layers`*".

L'illustrazione e l'elenco seguenti riassumono il flusso di lavoro generale per la creazione di un BSP.





1. *Configurazione del Sistema di Sviluppo Host per Supportare lo Sviluppo con Yocto Project:* Consultare la sezione "*Preparing the Build Host*" nel Manuale di Sviluppo dei Task di Yocto Project per le opzioni su come preparare un sistema per l'utilizzo di Yocto Project.
2. *Creare il Repository meta-intel sul Proprio Sistema:* Avere copie locali di questi layer BSP supportati sul proprio sistema dà accesso a layer utilizzabili durante la creazione del BSP. Per informazioni su come ottenere questi file, consultare la sezione "*Preparazione dell'Host di Build per Lavorare con i Layer BSP*".
3. *Creare il Proprio Layer BSP Utilizzando lo Script bitbake-layers:* I layer sono ideali per isolare e archiviare il lavoro per un determinato componente hardware. Un layer è essenzialmente una posizione o un'area in cui si inseriscono le ricette e le configurazioni per il BSP. Di fatto, un BSP è, di per sé, un tipo speciale di layer. Il modo più semplice per creare un nuovo layer BSP conforme a Yocto Project è utilizzare lo script bitbake-layers. Per informazioni su quello script, consultare la sezione "*Creazione di un Nuovo Layer BSP Tramite lo Script bitbake-layers*".

Un altro esempio che illustra un layer è un'applicazione. Supponiamo di creare un'applicazione che ha librerie o altre dipendenze necessarie per la compilazione e l'esecuzione. Il layer, in questo caso, sarebbe il luogo in cui sono memorizzate tutte le ricette che definiscono tali dipendenze. Il punto chiave di un layer è che si tratta di un'area isolata che contiene tutte le informazioni rilevanti per il progetto di cui il sistema di build OpenEmbedded è a conoscenza. Per ulteriori informazioni sui layer, consultare la sezione "*Il Modello a Layer di Yocto Project*" nel Manuale Introduttivo e Concetti di Yocto Project. È possibile fare riferimento anche alla sezione "*Comprendere e Creare i Layer*" nel Manuale di Sviluppo dei Task di Yocto Project. Per ulteriori informazioni sui layer BSP, consultare la sezione "*Layer BSP*".

#### **i** Nota

- Nella release di Yocto Project sono presenti quattro BSP di riferimento hardware, situati nel layer BSP `meta-yocto-bsp`:

- Texas Instruments Beaglebone (`beaglebone-yocto`)
- Due piattaforme IA generiche (`genericx86` e `genericx86-64`)
- Una piattaforma ARM 64 generica (`genericarm64`)

Quando si configura un layer per un nuovo BSP, è necessario seguire un layout standard. Questo layout è descritto nella sezione "[Esempio di Struttura del Filesystem](#)". Nel layout standard, si noti la struttura suggerita per le ricette e le informazioni di configurazione. È possibile visualizzare la struttura standard di un BSP esaminando qualsiasi BSP supportato presente nel layer `meta-intel`.

4. *Modificare la Configurazione del Nuovo Layer BSP:* La struttura standard di un layer BSP organizza i file da modificare in `conf` e in diverse directory `recipes-*` all'interno del layer BSP. Le modifiche alla configurazione identificano la posizione del nuovo layer sul sistema locale e il kernel che si intende utilizzare. Eseguendo lo script `bitbake-layers`, è possibile configurare interattivamente molti elementi del BSP (ad esempio, tastiera, touchscreen e così via).
5. *Modificare le Ricette del Nuovo Layer BSP:* Le modifiche alle ricette includono la modifica delle ricette (file `*.bb`), la rimozione delle ricette non utilizzate e l'aggiunta di nuove ricette o file di append (`.bbappend`) compatibili con l'hardware in uso.
6. *Preparazione per la Build:* Una volta apportate tutte le modifiche al layer BSP, restano alcune operazioni da eseguire affinché il sistema di build OpenEmbedded possa creare l'immagine. È necessario preparare l'ambiente di compilazione eseguendo uno script di configurazione dell'ambiente (ad esempio `oe-init-build-env`) e assicurarsi che due file di configurazione chiave siano configurati correttamente: il file `build/conf/local.conf` e il file `build/conf/bblayers.conf`. È necessario rendere il sistema di build OpenEmbedded a conoscenza del nuovo layer. Consultare la sezione "[Enabling Your Layer](#)" nel Manuale di Sviluppo dei Task di Yocto Project per informazioni su come far conoscere il nuovo layer al sistema di compilazione.
7. *Build dell'Immagine:* Il sistema di build OpenEmbedded utilizza il tool BitBake per compilare le immagini in base al tipo di immagine che si desidera creare. Ulteriori informazioni su BitBake sono disponibili nel [Manuale Utente di BitBake](#).

Il processo di build supporta diversi tipi di immagini per soddisfare esigenze differenti. Consultare il capitolo "[Immagini](#)" nel Manuale di Riferimento di Yocto Project per informazioni sulle immagini supportate.

## 7.1.5 Requisiti e Raccomandazioni per i BSP Rilasciati

Questa sezione descrive i requisiti e le raccomandazioni affinché un BSP rilasciato sia considerato conforme a Yocto Project.

### Requisiti per i BSP Rilasciati

Prima di esaminare i requisiti per i BSP, è opportuno considerare quanto segue:

- I requisiti qui descritti presuppongono che il layer BSP sia un layer "valido" e ben formato, che può essere aggiunto a Yocto Project. Per le linee guida sulla creazione di un layer che soddisfi questi requisiti di base, consultare la sezione "[Layer BSP](#)" in questo manuale e la sezione "[Comprendere e Creare i Layer](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

- I requisiti in questa sezione si applicano indipendentemente da come viene impacchettato un BSP. È necessario consultare le linee guida di impacchettamento e distribuzione per il proprio specifico processo di rilascio. Per un esempio di requisiti di packaging e distribuzione, consultare la pagina wiki "[Third Party BSP Release Process](#)".
- I requisiti per il BSP, così come viene reso disponibile a uno sviluppatore, sono completamente indipendenti dalla versione rilasciata del BSP. Ad esempio, i metadati del BSP possono essere contenuti in un repository Git e potrebbero avere una struttura di directory completamente diversa da quella presente nel layer BSP rilasciato ufficialmente.
- Non è richiesto che specifici pacchetti o modifiche di pacchetti siano presenti nel layer BSP, oltre ai requisiti generali di conformità con Yocto Project. Ad esempio, non esiste alcun requisito che imponga l'utilizzo di un kernel o di una versione del kernel specifici in un determinato BSP.

I requisiti per un BSP rilasciato conforme a Yocto Project sono:

- *Nome del Layer*: Il BSP deve avere un nome di layer che rispetti gli standard di Yocto Project. Per informazioni sui nomi dei layer BSP, consultare la sezione "[Layer BSP](#)".
- *Struttura del File System*: Quando possibile, utilizzare gli stessi nomi di directory nel layer BSP elencati nel file `recipes.txt`, che si trova nella directory `meta` di *OpenEmbedded-Core (OE-Core)*.

È necessario posizionare le ricette (file `*.bb`) e le modifiche alle ricette (file `*.bbappend`) nelle sottocartelle `recipes-*` in base all'area funzionale, come descritto in `recipes.txt`. Se non si trova una categoria in `recipes.txt` adatta a una particolare ricetta, è possibile creare una propria sottocartella `recipes-*`.

All'interno di una specifica categoria `recipes-*`, il layout deve corrispondere a quello presente nel repository Git *OpenEmbedded-Core (OE-Core)*. In altre parole, si devono posizionare i file correlati in sottocartelle `recipes-*` appropriate e specifiche per la funzione della ricetta, oppure all'interno di una sottocartella contenente un insieme di ricette strettamente correlate. Le ricette stesse devono seguire le linee guida generali per le ricette che si trovano nella "[Guida di Stile per le Ricette](#)" nella Guida per i Collaboratori di Yocto Project e di OpenEmbedded.

- *File di Licenza*: È necessario includere un file di licenza nella directory `meta-bsp_root_name`. Questa licenza copre i metadati BSP nel loro complesso. È necessario specificare quale licenza utilizzare poiché non ne esiste una predefinita. Vedere il file [COPYING.MIT](#) per il BSP Raspberry Pi nel layer BSP `meta-raspberrypi` come esempio.
- *File README*: È necessario includere un file `README` nella directory `meta-bsp_root_name`. Vedere il file [README.md](#) per il BSP Raspberry Pi nel layer BSP `meta-raspberrypi` come esempio.

Come minimo, il file `README` deve contenere quanto segue:

- Breve descrizione dell'hardware target.
- Elenco di tutte le dipendenze del BSP. Queste dipendenze sono in genere un elenco dei layer necessari per la compilazione del BSP. Tuttavia, l'elenco dovrebbe includere anche informazioni relative a qualsiasi altra dipendenza del BSP.
- Eventuali informazioni speciali relative alle licenze. Ad esempio, queste informazioni includono dettagli su variabili speciali necessarie per soddisfare un EULA (EULA, User License Agreement) o istruzioni su come compilare o distribuire i binari creati a partire dai metadati del BSP.

- Nome e recapiti del responsabile del layer BSP. Questa è la persona a cui inviare patch e domande. Per informazioni su come trovare la persona giusta, consultare la sezione [Apportare Modifiche a un Componente](#) della Guida per i Collaboratori di Yocto Project e di OpenEmbedded.
  - Istruzioni su come compilare il BSP utilizzando il layer BSP.
  - Istruzioni su come avviare la build del BSP dal layer BSP.
  - Istruzioni su come avviare le immagini binarie contenute nella directory `binary`, se presente.
  - Informazioni su eventuali bug o problemi noti di cui gli utenti dovrebbero essere a conoscenza durante la compilazione o l'avvio dei binari BSP.
- *File `README.sources`:* Se il BSP contiene immagini binarie nella directory `binary`, è necessario includere un file `README.sources` nella directory `meta-bsp_root_name`. Questo file specifica esattamente dove trovare i sorgenti utilizzati per generare le immagini binarie.
  - *File di Configurazione del layer:* È necessario includere un file `conf/layer.conf` nella directory `meta-bsp_root_name`. Questo file identifica il layer BSP `meta-bsp_root_name` come layer per il sistema di build.
  - *File di Configurazione della Macchina:* È necessario includere uno o più file `conf/machine/bsp_root_name.conf` nella directory `meta-bsp_root_name`. Questi file di configurazione definiscono le macchine target compilabili utilizzando il layer BSP. Più file di configurazione della macchina definiscono le varianti di configurazione della macchina supportate dal BSP. Se un BSP supporta più varianti di macchina, è necessario descrivere adeguatamente ciascuna variante nel file `README` del BSP. Non utilizzare più file di configurazione della macchina per descrivere hardware eterogeneo. Se si hanno target molto diversi, è necessario creare layer BSP separati per ciascun target.

** Nota**

È perfettamente possibile per uno sviluppatore strutturare il repository di lavoro come un insieme di file BSP non correlati e generare BSP destinati al rilascio da tale directory utilizzando script o altri meccanismi (ad esempio, il layer `meta-yocto-bsp`). Tali considerazioni esulano dall'ambito di questo documento.

## Raccomandazioni per i BSP Rilasciati

Ecco le raccomandazioni per i BSP rilasciati conformi a Yocto Project:

- *Immagini Avviabili:* I BSP rilasciati possono contenere una o più immagini avviabili [bootable]. L'inclusione di immagini avviabili consente agli utenti di provare facilmente il BSP utilizzando il proprio hardware.

In alcuni casi, potrebbe non essere conveniente includere un'immagine avviabile. In tal caso, si potrebbe rendere disponibili due versioni del BSP: una contenente immagini binarie e una senza. La versione senza immagini avviabili evita tempi di download inutili per gli utenti non interessati alle immagini.

Se è necessario distribuire un BSP e includere immagini avviabili o compilare kernel e filesystem destinati a consentire agli utenti di avviare il BSP a scopo di valutazione, è necessario inserire le immagini e gli artefatti in una sottocartella `binary/` situata nella directory `meta-bsp_root_name`.

**Nota**

Se si include un'immagine avviabile nel BSP e tale immagine è stata creata con software coperto da licenza GPL o altre licenze open source, è una propria responsabilità comprendere e rispettare tutti i requisiti di licenza, che potrebbero includere la distribuzione dei file sorgente.

- *Utilizzare un kernel Yocto Linux:* Le ricette del kernel nel BSP devono essere basate su un kernel Yocto Linux. Basare le ricette su questi kernel riduce i costi di manutenzione del BSP e ne aumenta la scalabilità. Consultare la categoria `Yocto Linux Kernel` nei repository sorgente di [Source Repositories](#) per questi kernel.

## 7.1.6 Personalizzazione di una Ricetta per un BSP

Se si intende personalizzare una ricetta per un BSP specifico, è necessario procedere come segue:

- Creare un file `*.bbappend` per la ricetta modificata. Per informazioni sull'utilizzo dei file di append, consultare la sezione *"Appending Other Layers Metadata With Your Layer"* nel Manuale di Sviluppo dei Task di Yocto Project.
- Assicurarsi che la struttura delle directory nel layer BSP che supporta la macchina sia tale da consentire al sistema di build OpenEmbedded di trovarla. Per ulteriori informazioni, consultare l'esempio riportato più avanti in questa sezione.
- Inserire il file di append in una directory il cui nome corrisponda al nome della macchina e che si trovi in una sottodirectory appropriata all'interno del layer BSP (ad esempio, `recipes-bsp`, `recipes-graphics`, `recipes-core` e così via).
- Inserire i file specifici del BSP nella directory corretta all'interno del layer BSP. La complessità del layer influisce sulla posizione in cui è necessario collocare questi file. Ad esempio, se il layer supporta diversi tipi di macchine, è necessario assicurarsi che la struttura delle directory del layer includa una gerarchia che separi i file in base alla macchina. Se il layer non supporta più macchine, non avrà questa gerarchia aggiuntiva e i file ovviamente non potranno risiedere in una directory specifica per la macchina.

Ecco un esempio specifico per aiutarti a comprendere meglio il processo. Questo esempio personalizza una ricetta aggiungendo un file di configurazione specifico per BSP denominato `interfaces` alla ricetta `init-ifupdown_1.0.bb` per la macchina "xyz", dove il layer BSP supporta anche diverse altre macchine:

1. Modificare il file `init-ifupdown_1.0.bbappend` in modo che contenga quanto segue:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/files:"
```

Il file di append deve trovarsi nella directory `meta-xyz/recipes-core/init-ifupdown`.

2. Creare e posizionare il nuovo file di configurazione `interfaces` nel layer del BSP qui:

```
meta-xyz/recipes-core/init-ifupdown/files/xyz-machine-one/interfaces
```

**i Nota**

Se il layer `meta-xyz` non supportasse più macchine, si deve posizionare il file di configurazione delle interfacce nel layer qui:

```
meta-xyz/recipes-core/init-ifupdown/files/interfaces
```

La variabile `FILESEXTRAPATHS` nei file di append estende il path di ricerca utilizzato dal sistema di build per trovare i file durante la compilazione. Di conseguenza, per questo esempio, è necessario che la directory `files` si trovi nella stessa posizione del file di append.

## 7.1.7 Considerazioni sulle Licenze BSP

In alcuni casi, un BSP contiene Intellectual Property (IP) [proprietà intellettuale] soggetta a licenza separata per uno o più componenti. In questi casi, è necessario accettare i termini di una licenza commerciale o di altro tipo che richieda un End User License Agreement (EULA) [Contratto di Licenza per l'Utente Finale] esplicito. Una volta accettata la licenza, il sistema di build OpenEmbedded può compilare e includere il componente corrispondente nell'immagine BSP finale. Se il BSP è disponibile come immagine precompilata, è possibile scaricarla dopo aver accettato la licenza o l'EULA.

Potrebbe accadere che alcuni componenti soggetti a licenza separata, essenziali per il normale funzionamento del sistema, non abbiano un sostituto libero da vincoli (o gratuito). Senza questi componenti essenziali, il sistema risulterebbe non funzionante. D'altra parte, potrebbe accadere che altri componenti soggetti a licenza, semplicemente "desiderabili" o facoltativi, abbiano un componente sostitutivo libero da vincoli che è possibile utilizzare al posto di accettare il componente soggetto a licenza separata. Anche per i componenti essenziali al sistema, potreste trovare un componente libero, non identico ma funzionante come versione con funzionalità ridotte rispetto alla versione con licenza presente nel file BSP.

Nei casi in cui è possibile sostituire un componente con uno libero mantenendo la funzionalità del sistema, la sezione "DOWNLOADS" nella scheda "SOFTWARE" del [Sito Web di Yocto Project](#), mette a disposizione file BSP privi di funzionalità e completamente esenti da vincoli di proprietà intellettuale. In questi casi, è possibile utilizzare direttamente la sostituzione senza ulteriori requisiti di licenza. Se presenti, questi file BSP privi di funzionalità hanno nomi diversi rispetto ai rispettivi file BSP con licenza. Se disponibili, queste sostituzioni rappresentano l'opzione più semplice e preferibile. Ovviamente, l'utilizzo di queste sostituzioni presuppone che la funzionalità risultante soddisfi i requisiti di sistema.

**i Nota**

Se, tuttavia, non è disponibile una versione libera o se questa offre funzionalità o qualità inadeguate, è possibile utilizzare una versione con licenza.

Nel sistema di build di OpenEmbedded esistono due metodi diversi per soddisfare i requisiti di licenza per un BSP gravato da vincoli. Il seguente elenco li descrive in ordine di preferenza:

1. *Utilizzare la Variabile `LICENSE_FLAGS` per Definire le Ricette che Contengono Pacchetti con Licenza Commerciale o di Altro Tipo:* Per ciascuna di queste ricette, è possibile specificare una stringa di licenza corrispondente in una variabile del file `build/conf/local.conf` denominata `LICENSE_FLAGS_ACCEPTED`. Specificare la stringa

di licenza corrispondente indica l'accettazione della licenza. In questo modo, il sistema di build può compilare la ricetta corrispondente e includere il componente nell'immagine. Per ulteriori dettagli sull'utilizzo di queste variabili, consultare la sezione "*Enabling Commercially Licensed Recipes*" nel Manuale di Sviluppo dei Task di Yocto Project.

Se si esegue la compilazione normalmente, senza specificare alcuna ricetta nella variabile `LICENSE_FLAGS_ACCEPTED`, la compilazione si interrompe e viene visualizzato l'elenco delle ricette che si è tentato di includere nell'immagine e che richiedono l'inserimento nella variabile `LICENSE_FLAGS_ACCEPTED`. Una volta inseriti i flag di licenza appropriati, riavviare la compilazione per riprendere da dove si era interrotta. Durante la compilazione, il prompt non verrà più visualizzato poiché il requisito è stato soddisfatto.

Una volta che i flag di licenza appropriati sono presenti nella whitelist della variabile `LICENSE_FLAGS_ACCEPTED`, è possibile compilare l'immagine vincolata senza apportare alcuna modifica al normale processo di compilazione.

2. *Ottenere una versione precompilata del BSP:* È possibile ottenere questo tipo di BSP selezionando la voce "DOWNLOADS" dalla scheda "SOFTWARE" sul [Sito Web di Yocto Project](#). È possibile scaricare i file tarball BSP contenenti componenti proprietari dopo aver accettato i termini di licenza di ciascun pacchetto, inclusi quelli con licenza, durante il processo di download. Ottenere il BSP in questo modo consente di accedere immediatamente a un'immagine con licenza dopo aver accettato i termini di licenza presentati dal sito web. Per compilare l'immagine autonomamente utilizzando le ricette contenute nel file tarball BSP, sarà comunque necessario creare un `LICENSE_FLAGS_ACCEPTED` appropriato per corrispondere alle ricette con licenza presenti nel BSP.

#### Nota

Le immagini precompilate includono un kernel a tempo limitato che viene eseguito per un periodo di tempo predeterminato (10 giorni) prima di forzare il riavvio del sistema. Questa limitazione ha lo scopo di scoraggiare la redistribuzione diretta dell'immagine. Per rimuovere questa restrizione, è necessario ricompilare l'immagine.

## 7.1.8 Creazione di un Nuovo Layer BSP Tramite lo Script `bitbake-layers`

Lo script `bitbake-layers create-layer` automatizza la creazione di un layer BSP. Un layer BSP è definito tale dalla presenza di almeno un file di configurazione della macchina. Inoltre, un layer BSP solitamente include una ricetta del kernel o un file di append che sfrutta una ricetta del kernel esistente. Il requisito principale, tuttavia, è la configurazione della macchina.

Seguire questi passaggi per creare un layer BSP:

- *Creazione di un Layer Generico:* Utilizzare lo script `bitbake-layers` con il sottocomando `create-layer` per creare un nuovo layer generico. Per istruzioni su come creare un layer generico utilizzando lo script `bitbake-layers`, consultare la sezione "*Creating Your Own Layer*" nel Manuale di Sviluppo dei Task di Yocto Project.
- *Creazione di un File di Configurazione del Layer:* Ogni layer necessita di un file di configurazione. Questo file di configurazione definisce la posizione delle ricette del layer, le priorità del layer e così via. È possibile trovare esempi di file `layer.conf` nei [Source Repositories](#) di Yocto Project. Per ottenere esempi di ciò che è necessario nel file di configurazione, individuare un layer (ad esempio "meta-ti") ed esaminare il file `layer.conf`.



- *Creare un File di Configurazione della Macchina:* Creare un file `conf/machine/bsp_root_name.conf`. Consultare `meta-yocto-bsp/conf/machine` per esempi di file `bsp_root_name.conf`. Esistono altri esempi, come `meta-ti` e `meta-freescale` di altri fornitori, che offrono esempi di configurazione e ottimizzazione più specifici per determinate macchine.
- *Creazione di una Ricetta del Kernel:* Creare una ricetta del kernel in `recipes-kernel/linux` utilizzando un file di aggiunta del kernel o un nuovo file di ricetta del kernel personalizzato (ad esempio `linux-yocto_6.12.bb`). Anche i layer BSP menzionati nel passaggio precedente contengono diversi esempi di kernel. Consultare la sezione "*Modifying an Existing Recipe*" nel Manuale di Sviluppo del Kernel Linux di Yocto Project per informazioni su come creare un kernel personalizzato.

La parte restante di questa sezione fornisce una descrizione del BSP di riferimento di Yocto Project per Beaglebone, che risiede nel layer `meta-yocto-bsp`.

## Esempio di Configurazione di un Layer BSP

La directory `conf` del layer contiene il file di configurazione `layer.conf`. In questo esempio, il file `conf/layer.conf` ha il seguente contenuto:

```
# We have a conf and classes directory, add to BBPATH
BBPATH .= ":${LAYERDIR}"

# We have a recipes directory containing .bb and .bbappend files, add to BBFILES
BBFILES += "${LAYERDIR}/recipes-*/*/*.bb \
           ${LAYERDIR}/recipes-*/*/*.bbappend"

BBFILE_COLLECTIONS += "yoctobsp"
BBFILE_PATTERN_yoctobsp = "^${LAYERDIR}/"
BBFILE_PRIORITY_yoctobsp = "5"
LAYERVERSION_yoctobsp = "4"
LAYERSERIES_COMPAT_yoctobsp = "blacksail"
```

Le variabili utilizzate in questo file configurano il layer. Un buon modo per imparare a conoscere i file di configurazione dei layer è esaminare i vari file BSP presenti nei repository sorgente di [Source Repositories](#).

Per una descrizione dettagliata di questo specifico file di configurazione del layer, consultare il "*passaggio 3*" nella sezione che descrive come creare layer nel Manuale di Sviluppo dei Task di Yocto Project.

## Esempio di Configurazione della Macchina BSP

Come accennato in precedenza in questa sezione, l'esistenza di almeno un file di configurazione della macchina è ciò che distingue un layer BSP da un layer generico o del kernel.

A titolo di esempio, si consideri il contenuto rilevante della directory `/meta-yocto/tree/meta-yocto-bsp/conf/` del layer BSP `meta-yocto-bsp`:

```
$ tree -F conf
conf/
|— layer.conf
```

(continues on next page)



(continua dalla pagina precedente)

```

└─ machine/
    ├── beaglebone-yocto.conf
    ├── genericarm64.conf
    ├── genericx86-64.conf
    ├── genericx86.conf
    └─ include/
        └─ genericx86-common.inc

```

che mostra quattro file di configurazione della macchina insieme a un file di configurazione di ottimizzazione di livello inferiore.

Le variabili utilizzate per configurare la macchina definiscono proprietà specifiche della macchina; ad esempio, pacchetti dipendenti dalla macchina, ottimizzazioni della macchina, il tipo di kernel da compilare e configurazioni di U-Boot.

L'elenco seguente fornisce alcune spiegazioni per le istruzioni presenti nel file di configurazione di riferimento di esempio per la scheda di sviluppo BeagleBone. Si tenga presente che è possibile definire molto altro all'interno di un file di configurazione della macchina. In generale, è possibile trovare informazioni sulle variabili correlate non presenti in questo esempio consultando "*Glossario delle Variabili*" nel Manuale di Riferimento di Yocto Project.

- **PREFERRED\_PROVIDER\_virtual/xserver**: La ricetta che fornisce "virtual/xserver" quando viene trovato più di un provider. In questo caso, la ricetta che fornisce "virtual/xserver" è "xserver-xorg", disponibile in `meta/recipes-graphics/xorg-xserver` in *OpenEmbedded-Core (OE-Core)*.
- **MACHINE\_EXTRA\_RRECOMMENDS**: Un elenco di pacchetti dipendenti dalla macchina non essenziali per l'avvio dell'immagine. Pertanto, la build non fallisce se i pacchetti non sono presenti. Tuttavia, i pacchetti sono necessari per un'immagine completa.

#### Suggerimento

Esistono numerose variabili `MACHINE*` che consentono di configurare un particolare componente hardware.

- **EXTRA\_IMAGEDEPENDS**: Ricette di compilazione che non forniscono pacchetti da installare nel filesystem di root, ma la cui creazione dell'immagine dipende da tali ricette. A volte una ricetta è necessaria per creare l'immagine finale, ma non è richiesta nel filesystem di root. In questo caso, la ricetta U-Boot deve essere compilata per l'immagine.

Alla fine del file, utilizziamo questa impostazione anche per implementare il supporto per `runqemu` sulla macchina host.

- **DEFAULTTUNE**: Le macchine utilizzano delle ottimizzazioni per migliorare le prestazioni della macchina, della CPU e delle applicazioni. Queste funzionalità, note collettivamente come "tuning features", sono impostate nel layer *OpenEmbedded-Core (OE-Core)* layer. In this example, the default tuning file is `tune-cortexa8`.

**i Nota**

L'istruzione include che carica il file `conf/machine/include/arm/tune-cortexa8.inc` offre numerose possibilità di ottimizzazione.

- **IMAGE\_FSTYPES**: I formati utilizzati dal sistema di build OpenEmbedded durante la creazione del filesystem root. In questo esempio, sono supportati quattro tipi di immagini.
- **EXTRA\_IMAGECMD**: Specifica opzioni aggiuntive per i comandi di creazione delle immagini. In questo esempio, l'opzione "-lnp" viene utilizzata durante la creazione dell'immagine JFFS2.
- **WKS\_FILE**: Il path del file *Wic kickstart* utilizzato dal sistema di build OpenEmbedded per creare un'immagine partizionata.
- `do_image_wic[depends]`: Un task che viene creato durante la compilazione. In questo esempio, il task dipende da strumenti specifici per creare il sysroot durante la compilazione di un'immagine Wic.
- **SERIAL\_CONSOLES**: Definisce una o più console seriali (TTY) da abilitare tramite getty.
- **PREFERRED\_PROVIDER\_virtual/kernel**: Specifica la ricetta che fornisce "virtual/kernel" quando viene trovato più di un provider. In questo caso, la ricetta che fornisce "virtual/kernel" è "linux-yocto", che si trova nella directory `recipes-kernel/linux`.
- **PREFERRED\_VERSION\_linux-yocto**: Definisce la versione della ricetta utilizzata per compilare il kernel, che in questo caso è "6.18%".
- **KERNEL\_IMAGETYPE**: Il tipo di kernel da compilare per il dispositivo. In questo caso, il sistema di build OpenEmbedded crea un'immagine di tipo "zImage".
- **KERNEL\_DEVICETREE**: I nomi dei device tree del kernel Linux generati (ovvero i file \*.dtb). Sono inclusi tutti i device tree per i vari dispositivi BeagleBone.
- **KERNEL\_EXTRA\_ARGS**: Argomenti aggiuntivi della riga di comando `make` che il sistema di build OpenEmbedded passa durante la compilazione del kernel. In questo esempio, `LOADADDR=${UBOOT_ENTRYPOINT}` viene passato come argomento della riga di comando.
- **SPL\_BINARY**: Definisce il tipo di binario del Secondary Program Loader (SPL). In questo caso, il binario SPL è impostato su "MLO", che sta per Multimedia card LOader.

La scheda di sviluppo BeagleBone richiede un SPL per l'avvio e il tipo di file SPL deve essere MLO. Di conseguenza, la configurazione della macchina deve definire **SPL\_BINARY** come MLO.

**i Nota**

Per ulteriori informazioni sull'utilizzo delle variabili SPL, consultare il file di inclusione `u-boot.inc`.

- **UBOOT\_\***: Definisce le varie configurazioni di U-Boot necessarie per creare un'immagine U-Boot. In questo esempio, è necessaria un'immagine U-Boot per avviare il dispositivo BeagleBone. Per ulteriori informazioni, consultare le seguenti variabili:
  - **UBOOT\_SUFFIX**: Indica l'estensione U-Boot generata.

- **UBOOT\_MACHINE**: Specifica il valore passato alla riga di comando make durante la creazione di un'immagine U-Boot.
- **MACHINE\_FEATURES**: Specifica l'elenco delle funzionalità hardware supportate dal dispositivo BeagleBone. In questo caso, il dispositivo supporta "usb gadget usb host vfat alsa".
- **IMAGE\_BOOT\_FILES**: File installati nella partizione di avvio del dispositivo durante la preparazione dell'immagine tramite lo strumento Wic con il plugin sorgente `bootimg_partition` o `bootimg_efi`.

## Esempio di Ricetta del Kernel BSP

La ricetta del kernel utilizzata per creare l'immagine del kernel per il dispositivo BeagleBone è stata definita nella configurazione della macchina:

```
PREFERRED_PROVIDER_virtual/kernel ?= "linux-yocto"
PREFERRED_VERSION_linux-yocto ?= "6.18%"
```

La directory `meta-yocto-bsp/recipes-kernel/linux` nel layer contiene i metadati utilizzati per la compilazione del kernel. In questo caso, viene utilizzato un file di append del kernel (ad esempio `linux-yocto_6.18.bbappend`) per sovrascrivere una ricetta del kernel esistente (ad esempio `linux-yocto_6.18.bb`), che si trova in <https://git.openembedded.org/openembedded-core/tree/meta/recipes-kernel/linux>.

Il contenuto del file di append è il seguente:

```
COMPATIBLE_MACHINE:genericarm64 = "genericarm64"
COMPATIBLE_MACHINE:beaglebone-yocto = "beaglebone-yocto"
COMPATIBLE_MACHINE:genericx86 = "genericx86"
COMPATIBLE_MACHINE:genericx86-64 = "genericx86-64"

KMACHINE:beaglebone-yocto ?= "beaglebone"
KMACHINE:genericx86 ?= "common-pc"
KMACHINE:genericx86-64 ?= "common-pc-64"

KBRANCH:genericarm64 ?= "v6.18/standard/genericarm64"
SRCREV_machine:genericarm64 ?= "5cd75b0b5da06045acdd0c66e50656ab82cb880f"
```

Questo particolare file di append funziona per tutte le macchine che fanno parte del layer `meta-yocto-bsp`. Le istruzioni pertinenti sono aggiunte con la stringa "beaglebone-yocto". Il sistema di build OpenEmbedded utilizza queste istruzioni per sovrascrivere istruzioni simili nella ricetta del kernel:

- **KBRANCH**: Identifica il branch del kernel che viene convalidato, patchato e configurato durante la build.
- **KMACHINE**: Identifica il nome della macchina come noto al kernel, che a volte è diverso dal nome noto al sistema di build OpenEmbedded.
- **SRCREV**: Identifica la revisione del codice sorgente utilizzato per creare l'immagine.
- **COMPATIBLE\_MACHINE**: Un'espressione regolare che si risolve in una o più macchine di destinazione con cui la ricetta è compatibile.

- [\*LINUX\\_VERSION\*](#): La versione di Linux da kernel.org utilizzata dal sistema di build OpenEmbedded per creare l'immagine del kernel.
- 

The Yocto Project ®

[<docs@lists.yoctoproject.org>](mailto:docs@lists.yoctoproject.org)

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.

---

## Manuale di Sviluppo dei Task di Yocto Project

---

### 8.1 Il Manuale di Sviluppo dei Task di Yocto Project

#### 8.1.1 Benvenuti!

Welcome to the Yocto Project Development Tasks Manual. This manual provides relevant procedures necessary for developing in the Yocto Project environment (i.e. developing embedded Linux images and user-space applications that run on targeted devices). This manual groups related procedures into higher-level sections. Procedures can consist of high-level steps or low-level steps depending on the topic.

Questo manuale fornisce quanto segue:

- Procedures that help you get going with the Yocto Project; for example, procedures that show you how to set up a build host and work with the Yocto Project source repositories.
- Procedures that show you how to submit changes to the Yocto Project. Changes can be improvements, new features, or bug fixes.
- Procedures related to "everyday" tasks you perform while developing images and applications using the Yocto Project, such as creating a new layer, customizing an image, writing a new recipe, and so forth.

Questo manuale non fornisce quanto segue:

- Redundant step-by-step instructions: For example, the *Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)* manual contains detailed instructions on how to install an SDK, which is used to develop applications for target hardware.
- Reference or conceptual material: This type of material resides in an appropriate reference manual. As an example, system variables are documented in the *Yocto Project Reference Manual*.

- Detailed public information not specific to the Yocto Project: For example, exhaustive information on how to use the Git version control system is better covered with Internet searches and official Git documentation than through the Yocto Project documentation.

### 8.1.2 Other Information

Because this manual presents information for many different topics, supplemental information is recommended for full comprehension. For introductory information on the Yocto Project, see the [Yocto Project Website](#). If you want to build an image with no knowledge of Yocto Project as a way of quickly testing it out, see the [Build Rapida di un'Immagine con lo Yocto Project](#) document.

For a comprehensive list of links and other documentation, see the "[Links and Related Documentation](#)" section in the Yocto Project Reference Manual.

## 8.2 Setting Up to Use the Yocto Project

This chapter provides guidance on how to prepare to use the Yocto Project. You can learn about creating a team environment to develop using the Yocto Project, how to set up a [build host](#), how to locate Yocto Project source repositories, and how to create local Git repositories.

### 8.2.1 Creating a Team Development Environment

It might not be immediately clear how you can use the Yocto Project in a team development environment, or how to scale it for a large team of developers. You can adapt the Yocto Project to many different use cases and scenarios; however, this flexibility could cause difficulties if you are trying to create a working setup that scales effectively.

To help you understand how to set up this type of environment, this section presents a procedure that gives you information that can help you get the results you want. The procedure is high-level and presents some of the project's most successful experiences, practices, solutions, and available technologies that have proved to work well in the past; however, keep in mind, the procedure here is simply a starting point. You can build off these steps and customize the procedure to fit any particular working environment and set of practices.

1. *Determine Who is Going to be Developing:* You first need to understand who is going to be doing anything related to the Yocto Project and determine their roles. Making this determination is essential to completing subsequent steps, which are to get your equipment together and set up your development environment's hardware topology.

Possible roles are:

- *Application Developer:* This type of developer does application level work on top of an existing software stack.
  - *Core System Developer:* This type of developer works on the contents of the operating system image itself.
  - *Build Engineer:* This type of developer manages Autobuilders and releases. Depending on the specifics of the environment, not all situations might need a Build Engineer.
  - *Test Engineer:* This type of developer creates and manages automated tests that are used to ensure all application and core system development meets desired quality standards.
2. *Gather the Hardware:* Based on the size and make-up of the team, get the hardware together. Ideally, any development, build, or test engineer uses a system that runs a supported Linux distribution. These systems, in

general, should be high performance (e.g. dual, six-core Xeons with 24 Gbytes of RAM and plenty of disk space). You can help ensure efficiency by having any machines used for testing or that run Autobuilders be as high performance as possible.

**i Nota**

Given sufficient processing power, you might also consider building Yocto Project development containers to be run under Docker, which is described later.

3. *Understand the Hardware Topology of the Environment:* Once you understand the hardware involved and the make-up of the team, you can understand the hardware topology of the development environment. You can get a visual idea of the machines and their roles across the development environment.
4. *Use Git as Your Source Control Manager (SCM):* Keeping your *Metadata* (i.e. recipes, configuration files, classes, and so forth) and any software you are developing under the control of an SCM system that is compatible with the *OpenEmbedded build system* is advisable. Of all of the SCMs supported by BitBake, the Yocto Project team strongly recommends using *Git*. Git is a distributed system that is easy to back up, allows you to work remotely, and then connects back to the infrastructure.

**i Nota**

For information about BitBake, see the [BitBake User Manual](#).

It is relatively easy to set up Git services and create infrastructure like <https://git.yoctoproject.org/>, which is based on server software called *Gitolite* with *cggit* being used to generate the web interface that lets you view the repositories. *gitolite* identifies users using SSH keys and allows branch-based access controls to repositories that you can control as little or as much as necessary.

5. *Set up the Application Development Machines:* As mentioned earlier, application developers are creating applications on top of existing software stacks. Here are some best practices for setting up machines used for application development:
  - Use a pre-built toolchain that contains the software stack itself. Then, develop the application code on top of the stack. This method works well for small numbers of relatively isolated applications.
  - Keep your cross-development toolchains updated. You can do this through provisioning either as new toolchain downloads or as updates through a package update mechanism to provide updates to an existing toolchain. The exact mechanics of how and when to do this depend on local policy.
  - Use multiple toolchains installed locally into different locations to allow development across versions.
6. *Set up the Core Development Machines:* As mentioned earlier, core developers work on the contents of the operating system itself. Here are some best practices for setting up machines used for developing images:
  - Have the *OpenEmbedded Build System* available on the developer workstations so developers can run their own builds and directly rebuild the software stack.

- Keep the core system unchanged as much as possible and do your work in layers on top of the core system. Doing so gives you a greater level of portability when upgrading to new versions of the core system or Board Support Packages (BSPs).
- Share layers amongst the developers of a particular project and contain the policy configuration that defines the project.

7. *Set up an Autobuilder:* Autobuilders are often the core of the development environment. It is here that changes from individual developers are brought together and centrally tested. Based on this automated build and test environment, subsequent decisions about releases can be made. Autobuilders also allow for "continuous integration" style testing of software components and regression identification and tracking.

See "[Yocto Project Autobuilder](#)" for more information and links to buildbot. The Yocto Project team has found this implementation works well in this role. A public example of this is the Yocto Project Autobuilders, which the Yocto Project team uses to test the overall health of the project.

The features of this system are:

- Highlights when commits break the build.
- Populates an *sstate cache* from which developers can pull rather than requiring local builds.
- Allows commit hook triggers, which trigger builds when commits are made.
- Allows triggering of automated image booting and testing under the Quick EMUlator (QEMU).
- Supports incremental build testing and from-scratch builds.
- Shares output that allows developer testing and historical regression investigation.
- Creates output that can be used for releases.
- Allows scheduling of builds so that resources can be used efficiently.

8. *Set up Test Machines:* Use a small number of shared, high performance systems for testing purposes. Developers can use these systems for wider, more extensive testing while they continue to develop locally using their primary development system.

9. *Document Policies and Change Flow:* The Yocto Project uses a hierarchical structure and a pull model. There are scripts to create and send pull requests (i.e. `create-pull-request` and `send-pull-request`). This model is in line with other open source projects where maintainers are responsible for specific areas of the project and a single maintainer handles the final "top-of-tree" merges.

 **Nota**

You can also use a more collective push model. The `gitolite` software supports both the push and pull models quite easily.

As with any development environment, it is important to document the policy used as well as any main project guidelines so they are understood by everyone. It is also a good idea to have well-structured commit messages, which are usually a part of a project's guidelines. Good commit messages are essential when looking back in time and trying to understand why changes were made.



If you discover that changes are needed to the core layer of the project, it is worth sharing those with the community as soon as possible. Chances are if you have discovered the need for changes, someone else in the community needs them also.

10. *Development Environment Summary*: Aside from the previous steps, here are best practices within the Yocto Project development environment:

- Use *Git* as the source control system.
- Maintain your Metadata in layers that make sense for your situation. See the "*Il Modello a Layer di Yocto Project*" section in the Yocto Project Overview and Concepts Manual and the "*Comprendere e Creare i Layer*" section for more information on layers.
- Separate the project's Metadata and code by using separate Git repositories. See the "*I Repository del Codice Sorgente di Yocto Project*" section in the Yocto Project Overview and Concepts Manual for information on these repositories. See the "*Setting Up the Poky Reference Distro Manually*" section for information on how to set up local Git repositories for related upstream Yocto Project Git repositories.
- Set up the directory for the shared state cache (*SSTATE\_DIR*) where it makes sense. For example, set up the sstate cache on a system used by developers in the same organization and share the same source directories on their machines.
- Set up a local *Equivalenza degli Hash* server.

See the *Equivalenza degli Hash* section of the Yocto Project Overview and Concepts Manual for more details on the hash equivalence feature.

See the *Setting up a Hash Equivalence Server* section of the Yocto Project Development Tasks Manual for details on how to set up a *Equivalenza degli Hash* server.

- Set up an Autobuilder and have it populate the sstate cache and source directories.
- The Yocto Project community encourages you to send patches to the project to fix bugs or add features. If you do submit patches, follow the project commit guidelines for writing good commit messages. See the "*Apportare Modifiche a un Componente*" section in the Yocto Project and OpenEmbedded Contributor Guide.
- Send changes to the core sooner than later as others are likely to run into the same issues. For some guidance on mailing lists to use, see the lists in the "*Trovare una Mailing List Adatta*" section. For a description of the available mailing lists, see the "*Mailing lists*" section in the Yocto Project Reference Manual.

## 8.2.2 Preparing the Build Host

This section provides procedures to set up a system to be used as your *Build Host* for development using the Yocto Project. Your build host can be a native Linux machine (recommended), it can be an *OCI container* (such as *Docker* or *Podman*), or it can be a Windows machine capable of running version 2 of Windows Subsystem For Linux (WSL 2).

**i Nota**

The Yocto Project is not compatible with version 1 of [Windows Subsystem for Linux](#). It is compatible but neither officially supported nor validated with WSL 2. If you still decide to use WSL please upgrade to [WSL 2](#).

Once your build host is set up to use the Yocto Project, further steps are necessary depending on what you want to accomplish. See the following references for information on how to prepare for Board Support Package (BSP) development and kernel development:

- *BSP Development:* See the "[Preparazione dell'Host di Build per Lavorare con i Layer BSP](#)" section in the Yocto Project Board Support Package (BSP) Developer's Guide.
- *Kernel Development:* See the "[Preparazione dell'Host di Build per Lavorare sul Kernel](#)." section in the Yocto Project Linux Kernel Development Manual.

## Setting Up a Native Linux Host

Follow these steps to prepare a native Linux machine as your Yocto Project Build Host:

1. *Use a Supported Linux Distribution:* You should have a reasonably current Linux-based host system. You will have the best results with a recent release of Fedora, openSUSE, Debian, Ubuntu, RHEL or CentOS as these releases are frequently tested against the Yocto Project and officially supported. For a list of the distributions under validation and their status, see the "[Supported Linux Distributions](#)" section in the Yocto Project Reference Manual.
2. *Have Enough Free Memory:* Your system should have at least 50 Gbytes of free disk space for building images.
3. *Meet Minimal Version Requirements:* The OpenEmbedded build system should be able to run on any modern distribution that has the following versions for Git, tar, Python, gcc and make.
  - Git 2.22.0 o superiore
  - tar 1.28 o superiore
  - Python 3.9.0 or greater.
  - gcc 10.1 or greater.
  - GNU make 4.0 o superiore

If your build host does not satisfy all of these listed version requirements, you can take steps to prepare the system so that you can still use the Yocto Project. See the "[Versioni richieste di Git, tar, Python, make e gcc](#)" section in the Yocto Project Reference Manual for information.

4. *Install Development Host Packages:* Required development host packages vary depending on your build host and what you want to do with the Yocto Project. Collectively, the number of required packages is large if you want to be able to cover all cases.

For lists of required packages for all scenarios, see the "[Pacchetti Richiesti per l'Host di Build](#)" section in the Yocto Project Reference Manual.

Once you have completed the previous steps, you are ready to continue using a given development path on your native Linux machine. If you are going to use BitBake, see the "[Preparing the Poky Reference Distro](#)" section. If you are going to use the Extensible SDK, see the "[Using the Extensible SDK](#)" Chapter in the Yocto Project Application

Development and the Extensible Software Development Kit (eSDK) manual. If you want to work on the kernel, see the *Manuale di Sviluppo del Kernel Linux di Yocto Project*. If you are going to use Toaster, see the "*Configurazione e Utilizzo di Toaster*" section in the Toaster User Manual. If you are a VSCode user, you can configure the *Yocto Project BitBake* extension accordingly.

## Setting Up to Use Windows Subsystem For Linux (WSL 2)

With *Windows Subsystem for Linux (WSL 2)*, you can create a Yocto Project development environment that allows you to build on Windows. You can set up a Linux distribution inside Windows in which you can develop using the Yocto Project.

Follow these general steps to prepare a Windows machine using WSL 2 as your Yocto Project build host:

1. *Make sure your Windows machine is capable of running WSL 2:*

While all Windows 11 and Windows Server 2022 builds support WSL 2, the first versions of Windows 10 and Windows Server 2019 didn't. Check the minimum build numbers for *Windows 10* and for *Windows Server 2019*.

To check which build version you are running, you may open a command prompt on Windows and execute the command "ver":

```
C:\Users\myuser> ver

Microsoft Windows [Version 10.0.19041.153]
```

2. *Install the Linux distribution of your choice inside WSL 2:* Once you know your version of Windows supports WSL 2, you can install the distribution of your choice from the Microsoft Store. Open the Microsoft Store and search for Linux. While there are several Linux distributions available, the assumption is that your pick will be one of the distributions supported by the Yocto Project as stated on the instructions for using a native Linux host. After making your selection, simply click "Get" to download and install the distribution.
3. *Check which Linux distribution WSL 2 is using:* Open a Windows PowerShell and run:

```
C:\WINDOWS\system32> wsl -l -v

NAME      STATE      VERSION
*Ubuntu   Running    2
```

Note that WSL 2 supports running as many different Linux distributions as you want to install.

4. *Optionally Get Familiar with WSL:* You can learn more on <https://docs.microsoft.com/en-us/windows/wsl/wsl2-about>.
5. *Launch your WSL Distribution:* From the Windows start menu simply launch your WSL distribution just like any other application.
6. *Optimize your WSL 2 storage often:* Due to the way storage is handled on WSL 2, the storage space used by the underlying Linux distribution is not reflected immediately, and since BitBake heavily uses storage, after several builds, you may be unaware you are running out of space. As WSL 2 uses a VHDX file for storage, this issue can be easily avoided by regularly optimizing this file in a manual way:

1. *Find the location of your VHDX file:*

First you need to find the distro app package directory, to achieve this open a Windows Powershell as Administrator and run:

```
C:\WINDOWS\system32> Get-AppxPackage -Name "*Ubuntu*" | Select-Object PackageFamilyName
PackageFamilyName
-----
CanonicalGroupLimited.UbuntuonWindows_79abcdefg
```

You should now replace the PackageFamilyName and your user on the following path to find your VHDX file:

```
ls C:\Users\myuser\AppData\Local\Packages\CanonicalGroupLimited.
    ↳ UbuntuonWindows_79abcdefg\LocalState\
Mode                LastWriteTime         Length Name
----                -
-a-----          3/14/2020   9:52 PM       57418973184 ext4.vhdx
```

Your VHDX file path is: C:\Users\myuser\AppData\Local\Packages\CanonicalGroupLimited.UbuntuonWindows\_79abcdefg\LocalState\ext4.vhdx

#### 2a. Optimize your VHDX file using Windows Powershell:

To use the `optimize-vhd` cmdlet below, first install the Hyper-V option on Windows. Then, open a Windows Powershell as Administrator to optimize your VHDX file, shutting down WSL first:

```
C:\WINDOWS\system32> wsl --shutdown
C:\WINDOWS\system32> optimize-vhd -Path C:\Users\myuser\AppData\Local\
    ↳ Packages\CanonicalGroupLimited.UbuntuonWindows_79abcdefg\LocalState\
    ↳ ext4.vhdx -Mode full
```

A progress bar should be shown while optimizing the VHDX file, and storage should now be reflected correctly on the Windows Explorer.

#### 2b. Optimize your VHDX file using DiskPart:

The `optimize-vhd` cmdlet noted in step 2a above is provided by Hyper-V. Not all SKUs of Windows can install Hyper-V. As an alternative, use the DiskPart tool. To start, open a Windows command prompt as Administrator to optimize your VHDX file, shutting down WSL first:

```
C:\WINDOWS\system32> wsl --shutdown
C:\WINDOWS\system32> diskpart

DISKPART> select vdisk file="<path_to_VHDX_file>"
DISKPART> attach vdisk readonly
DISKPART> compact vdisk
DISKPART> detach
DISKPART> exit
```

**i Nota**

The current implementation of WSL 2 does not have out-of-the-box access to external devices such as those connected through a USB port, but it automatically mounts your C: drive on `/mnt/c/` (and others), which you can use to share deploy artifacts to be later flashed on hardware through Windows, but your *Build Directory* should not reside inside this mountpoint.

Once you have WSL 2 set up, everything is in place to develop just as if you were running on a native Linux machine. If you are going to use the Extensible SDK container, see the "*Using the Extensible SDK*" Chapter in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual. If you are going to use the Toaster container, see the "*Configurazione e Utilizzo di Toaster*" section in the Toaster User Manual. If you are a VSCode user, you can configure the *Yocto Project BitBake* extension accordingly.

## Preparing the Poky Reference Distro

Now that the *Build Host* has been prepared to build images, the next step can be to build the *Poky* reference distro. There are two ways of setting up the *Poky* reference distro:

- Utilizzando l'utilità da riga di comando `bitbake-setup` di *BitBake*. Seguire le istruzioni riportate in:

*Setting Up The Environment With bitbake-setup*

- Clonando manualmente i repository necessari. Seguire le istruzioni riportate in:

*Setting Up the Poky Reference Distro Manually*

**i Nota**

The *Poky* distro is a reference distro. It can be used to try the Yocto Project but should not be used in a production environment. Instead, it is recommended to create your own distro, see the *Creating Your Own Distribution* section of the Yocto Project Development Tasks Manual.

## Initializing the Build Environment

Initializing the build environment is a common task, as it needs to be done for each new instance of the shell where the *Poky* reference distro was set up:

- If `bitbake-setup` was used to set up the *Poky* reference distro, you need to source the `init-build-env` file of the *Setup* directory that was created after the `bitbake-setup init` command execution:

```
$ source <setup-dir>/build/init-build-env
```

- If the *Poky* distro was set up using manual clones of the layers, you need to source the `oe-init-build-env` script present in the *OpenEmbedded-Core (OE-Core)* layer:

```
$ source openembedded-core/oe-init-build-env
```

This will set up your current shell and change the current working directory to the *Build Directory*.

## Where To Go From Here

- Configure your build: follow *Configurazione Utente*.
- Learn how and what to build with *BitBake*: follow *Building*.

## 8.3 Comprendere e Creare i Layer

The OpenEmbedded build system supports organizing *Metadata* into multiple layers. Layers allow you to isolate different types of customizations from each other. For introductory information on the Yocto Project Layer Model, see the "*Il Modello a Layer di Yocto Project*" section in the Yocto Project Overview and Concepts Manual.

Note well that to properly call the `bitbake-layers` command explained below, you must first *initialize the build environment* using your project's environment setup script. Without an initialized environment, your shell would not know where to find the command or your build configuration.

### 8.3.1 Creating Your Own Layer

Follow these general steps to create your layer without using tools:

1. *Check Existing Layers*: Before creating a new layer, you should be sure someone has not already created a layer containing the Metadata you need. You can see the [OpenEmbedded Metadata Index](#) for a list of layers from the OpenEmbedded community that can be used in the Yocto Project. You could find a layer that is identical or close to what you need.

#### Nota

For information on BSP layers, see the "*Layer BSP*" section in the Yocto Project Board Specific (BSP) Developer's Guide.

2. *Create a new Layer*: Create the directory for your layer. The `bitbake-layers` script with the `create-layer` subcommand simplifies creating a new general layer. Place it next to the other layers in your *Source Directory*.

In its simplest form, you can use the following command to create a layer named "your\_layer\_name" in the current directory:

```
$ bitbake-layers create-layer your_layer_name
```

While not strictly required, prepend the name of the directory with the string "meta-". For example:

```
meta-mylayer
meta-GUI_xyz
meta-mymachine
```

With rare exceptions, a layer's name follows this form:

```
meta-root_name
```

Following this layer naming convention can save you trouble later when tools, components, or variables "assume" your layer name begins with "meta-". A notable example is in configuration files as shown in the following step where layer names without the "meta-" string are appended to several variables used in the configuration.

As an example, the following command creates a layer named `meta-scottrif` in your current directory:

```
$ bitbake-layers create-layer meta-scottrif
NOTE: Starting bitbake server...
Add your new layer with 'bitbake-layers add-layer meta-scottrif'
```

In order to use a layer with the *OpenEmbedded Build System*, you need to add the layer to your `build/conf/bblayers.conf` configuration file, as hinted by the previous command. See the "*Aggiungere un Layer Utilizzando lo Script bitbake-layers*" section for more information.

By default, the `bitbake-layers create-layer` command creates a layer with the following:

- A `conf/layer.conf` configuration file with default definitions.

Here is an explanation of the typical content of the layer configuration file:

- **BBPATH**: Adds the layer's root directory to BitBake's search path. Through the use of the **BBPATH** variable, BitBake locates class files (`.bbclass`), configuration files, and files that are included with `include` and `require` statements. For these cases, BitBake uses the first file that matches the name found in **BBPATH**. This is similar to the way the `PATH` variable is used for binaries. It is recommended, therefore, that you use unique class and configuration filenames in your custom layer.

See the *Locating Include Files* section of the BitBake User Manual for more details on how files are included with *BitBake*.

- **BBFILES**: Defines the location for all recipes in the layer.
- **BBFILE\_COLLECTIONS**: Establishes the current layer through a unique identifier that is used throughout the *OpenEmbedded Build System* to refer to the layer. In this example, the identifier "yoctobsp" is the representation for the container layer named "meta-yocto-bsp".

This name is used by other layers when specifying the layer dependencies via the **LAYERDEPENDS** variable.

- **BBFILE\_PATTERN**: Expands immediately during parsing to provide the directory of the layer.
- **BBFILE\_PRIORITY**: Establishes a priority to use for recipes in the layer when the *OpenEmbedded Build System* finds recipes of the same name in different layers.
- **LAYERVERSION**: Establishes a version number for the layer. You can use this version number to specify this exact version of the layer as a dependency when using the **LAYERDEPENDS** variable.
- **LAYERDEPENDS**: Lists all layers on which this layer depends (if any). It uses the layer names specified by the **BBFILE\_COLLECTIONS** variable.
- **LAYERSERIES\_COMPAT**: Lists the Yocto Project release codenames (in lowercase) this layer is compatible with. For example: "blacksail".

This variable is a good way to indicate if a particular layer is current.



- A `recipes-example` subdirectory that itself contains a subdirectory named `example`, which contains an `example.bb` recipe file.
- A `COPYING.MIT`, which is the license statement for the layer. The script assumes you want to use the MIT license, which is typical for most layers, for the contents of the layer itself.
- A `README` file, which is a file describing the contents of your new layer.

If you want to set the priority of the layer to other than the default value of "6", you can either use the `--priority` option or you can edit the `BBFILE_PRIORITY` value in the `conf/layer.conf` after the script creates it. Furthermore, if you want to give the example recipe file some name or version other than the defaults, you can use the `--example-recipe-name` and/or `--example-recipe-version` options.

The easiest way to see how the `bitbake-layers create-layer` command works is to experiment with the script. You can also read the usage information by running `bitbake-layers create-layer --help`.

3. *Add Content:* Depending on the type of layer, add the content. If the layer adds support for a machine, add the machine configuration in a `conf/machine/` file within the layer. If the layer adds distro policy, add the distro configuration in a `conf/distro/` file within the layer. If the layer introduces new recipes, put the recipes you need in `recipes-*` subdirectories within the layer.

#### Nota

For an explanation of layer hierarchy that is compliant with the Yocto Project, see the "*Esempio di Struttura del Filesystem*" section in the Yocto Project Board Support Package (BSP) Developer's Guide.

4. *Optionally Test for Compatibility:* If you want permission to use the Yocto Project Compatibility logo with your layer or application that uses your layer, perform the steps to apply for compatibility. See the "*Making Sure Your Layer is Compatible With Yocto Project*" section for more information.

## 8.3.2 Following Best Practices When Creating Layers

To create layers that are easier to maintain and that will not impact builds for other machines, you should consider the information in the following list:

- *Avoid "Overlaying" Entire Recipes from Other Layers in Your Configuration:* In other words, do not copy an entire recipe into your layer and then modify it. Rather, use an append file (`.bbappend`) to override only those parts of the original recipe you need to modify.
- *Avoid Duplicating Include Files:* Use append files (`.bbappend`) for each recipe that uses an include file. Or, if you are introducing a new recipe that requires the included file, use the path relative to the original layer directory to refer to the file. For example, use `require recipes-core/package/file.inc` instead of `require file.inc`. If you're finding you have to overlay the include file, it could indicate a deficiency in the include file in the layer to which it originally belongs. If this is the case, you should try to address that deficiency instead of overlaying the include file. For example, you could address this by getting the maintainer of the include file to add a variable or variables to make it easy to override the parts needing to be overridden.
- *Structure Your Layers:* Proper use of overrides within append files and placement of machine-specific files within your layer can ensure that a build is not using the wrong Metadata and negatively impacting a build for a different machine. Here are some examples:



- *Modify Variables to Support a Different Machine:* Suppose you have a layer named `meta-one` that adds support for building machine "one". To do so, you use an append file named `base-files.bbappend` and create a dependency on "foo" by altering the `DEPENDS` variable:

```
DEPENDS = "foo"
```

The dependency is created during any build that includes the layer `meta-one`. However, you might not want this dependency for all machines. For example, suppose you are building for machine "two" but your `build/conf/bblayers.conf` file has the `meta-one` layer included. During the build, the `base-files` for machine "two" will also have the dependency on `foo`.

To make sure your changes apply only when building machine "one", use a machine override with the `DEPENDS` statement:

```
DEPENDS:one = "foo"
```

You should follow the same strategy when using `:append` and `:prepend` operations:

```
DEPENDS:append:one = " foo"
DEPENDS:prepend:one = "foo "
```

As an actual example, here's a snippet from the generic kernel include file `linux-yocto.inc`, wherein the kernel compile and link options are adjusted in the case of a subset of the supported architectures:

```
DEPENDS:append:aarch64 = " libgcc"
KERNEL_CC:append:aarch64 = " ${TOOLCHAIN_OPTIONS}"
KERNEL_LD:append:aarch64 = " ${TOOLCHAIN_OPTIONS}"

DEPENDS:append:nios2 = " libgcc"
KERNEL_CC:append:nios2 = " ${TOOLCHAIN_OPTIONS}"
KERNEL_LD:append:nios2 = " ${TOOLCHAIN_OPTIONS}"

DEPENDS:append:arc = " libgcc"
KERNEL_CC:append:arc = " ${TOOLCHAIN_OPTIONS}"
KERNEL_LD:append:arc = " ${TOOLCHAIN_OPTIONS}"

KERNEL_FEATURES:append:qemuall = " features/debug/printk.scc"
```

- *Place Machine-Specific Files in Machine-Specific Locations:* When you have a base recipe, such as `base-files.bb`, that contains a `SRC_URI` statement to a file, you can use an append file to cause the build to use your own version of the file. For example, an append file in your layer at `meta-one/recipes-core/base-files/base-files.bbappend` could extend `FILESPATH` using `FILESEXTRAPATHS` as follows:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${BPN}:"
```

The build for machine "one" will pick up your machine-specific file as long as you have the file in `meta-one/recipes-core/base-files/base-files/`. However, if you are building for a different

machine and the [build/conf/bblayers.conf](#) file includes the `meta-one` layer and the location of your machine-specific file is the first location where that file is found according to [FILESPATH](#), builds for all machines will also use that machine-specific file.

You can make sure that a machine-specific file is used for a particular machine by putting the file in a subdirectory specific to the machine. For example, rather than placing the file in `meta-one/recipes-core/base-files/base-files/` as shown above, put it in `meta-one/recipes-core/base-files/base-files/one/`. Not only does this make sure the file is used only when building for machine "one", but the build process locates the file more quickly.

In summary, you need to place all files referenced from [SRC\\_URI](#) in a machine-specific subdirectory within the layer in order to restrict those files to machine-specific builds.

- *Perform Steps to Apply for Yocto Project Compatibility:* If you want permission to use the Yocto Project Compatibility logo with your layer or application that uses your layer, perform the steps to apply for compatibility. See the "[Making Sure Your Layer is Compatible With Yocto Project](#)" section for more information.
- *Follow the Layer Naming Convention:* Store custom layers in a Git repository that use the `meta-layer_name` format.
- *Group Your Layers Locally:* Clone your repository alongside other layers in your [Source Directory](#).

### 8.3.3 Making Sure Your Layer is Compatible With Yocto Project

When you create a layer used with the Yocto Project, it is advantageous to make sure that the layer interacts well with existing Yocto Project layers (i.e. the layer is compatible with the Yocto Project). Ensuring compatibility makes the layer easy to be consumed by others in the Yocto Project community and could allow you permission to use the Yocto Project Compatible Logo.

#### Nota

Only Yocto Project member organizations are permitted to use the Yocto Project Compatible Logo. The logo is not available for general use. For information on how to become a Yocto Project member organization, see the [Yocto Project Website](#).

The Yocto Project Compatibility Program consists of a layer application process that requests permission to use the Yocto Project Compatibility Logo for your layer and application. The process consists of two parts:

1. Successfully passing a script (`yocto-check-layer`) that, when run against your layer, tests it against constraints based on experiences of how layers have worked in the real world and where pitfalls have been found. Getting a "PASS" result from the script is required for successful compatibility registration.
2. Completion of an application acceptance form, which you can find at <https://www.yoctoproject.org/compatible-registration/>.

To be granted permission to use the logo, you need to satisfy the following:

- Be able to check the box indicating that you got a "PASS" when running the script against your layer.
- Answer "Yes" to the questions on the form or have an acceptable explanation for any questions answered "No".
- Be a Yocto Project Member Organization.

The remainder of this section presents information on the registration form and on the `yocto-check-layer` script.

## Yocto Project Compatible Program Application

Use the form to apply for your layer's approval. Upon successful application, you can use the Yocto Project Compatibility Logo with your layer and the application that uses your layer.

To access the form, use this link: <https://www.yoctoproject.org/compatible-registration>. Follow the instructions on the form to complete your application.

The application consists of the following sections:

- *Contact Information:* Provide your contact information as the fields require. Along with your information, provide the released versions of the Yocto Project for which your layer is compatible.
- *Acceptance Criteria:* Provide "Yes" or "No" answers for each of the items in the checklist. There is space at the bottom of the form for any explanations for items for which you answered "No".
- *Recommendations:* Provide answers for the questions regarding Linux kernel use and build success.

## yocto-check-layer Script

The `yocto-check-layer` script provides you a way to assess how compatible your layer is with the Yocto Project. You should run this script prior to using the form to apply for compatibility as described in the previous section. You need to achieve a "PASS" result in order to have your application form successfully processed.

The script divides tests into three areas: COMMON, BSP, and DISTRO. For example, given a distribution layer (DISTRO), the layer must pass both the COMMON and DISTRO related tests. Furthermore, if your layer is a BSP layer, the layer must pass the COMMON and BSP set of tests.

To execute the script, enter the following commands from your build directory:

```
$ source oe-init-build-env
$ yocto-check-layer your_layer_directory
```

Be sure to provide the actual directory for your layer as part of the command.

You should pass the dependencies of your layer using the `--dependency` argument:

```
$ source oe-init-build-env
$ yocto-check-layer --dependency <layer1_directory> <layer2_directory> ... -- your_
↳ layer_directory
```

For *BSP* layers, the `--machines` argument should be passed as part of the command:

```
$ source oe-init-build-env
$ yocto-check-layer --machines <machine1> <machine2> ... -- your_layer_directory
```

These machines are the ones present in your BSP layer, in the `conf/machine/` directory.

Entering the command causes the script to determine the type of layer and then to execute a set of specific tests against the layer.

The following list overviews the test:

- `common.test_readme`: Tests if a `README` file exists in the layer and the file is not empty.
- `common.test_security`: Tests that the layer has a `SECURITY.md` (or similar) file, either in the layer itself or at the top of the containing git repository.
- `common.test_parse`: Tests to make sure that BitBake can parse the files without error (i.e. `bitbake -p`).
- `common.test_show_environment`: Tests that the global or per-recipe environment is in order without errors (i.e. `bitbake -e`).
- `common.test_world`: Verifies that `bitbake world` works.
- `common.test_world_inherit_class`: Verifies that `bitbake world` works when the *yocto-check-layer* class is inherited.
- `common.test_patches_upstream_status`: Verifies that all the patch files included in the layer contain a *Stato della Patch Upstream*.
- `common.test_signatures`: Tests to be sure that BSP and DISTRO layers do not come with recipes that change signatures.
- `common.test_layerseries_compat`: Verifies layer compatibility is set properly.
- `bsp.test_bsp_defines_machines`: Tests if a BSP layer has machine configurations.
- `bsp.test_bsp_no_set_machine`: Tests to ensure a BSP layer does not set the machine when the layer is added.
- `bsp.test_machine_world`: Verifies that `bitbake world` works regardless of which machine is selected.
- `bsp.test_machine_signatures`: Verifies that building for a particular machine affects only the signature of tasks specific to that machine.
- `distro.test_distro_defines_distros`: Tests if a DISTRO layer has distro configurations.
- `distro.test_distro_no_set_distros`: Tests to ensure a DISTRO layer does not set the distribution when the layer is added.

For a complete list of tests, see the `scripts/lib/checklayer/cases` directory in *OpenEmbedded-Core (OE-Core)*.

### 8.3.4 Enabling Your Layer

Before the OpenEmbedded build system can use your new layer, you need to enable it. To enable your layer, simply add your layer's path to the `BBLAYERS` variable in your `build/conf/bblayers.conf` file, which is found in the *Build Directory*. The following example shows how to enable your new `meta-mylayer` layer (note how your new layer exists outside of the official `poky` repository which you would have checked out earlier):

```
# POKY_BBLAYERS_CONF_VERSION is increased each time build/conf/bblayers.conf
# changes incompatibly
POKY_BBLAYERS_CONF_VERSION = "2"
BBPATH = "${TOPDIR}"
BBFILES ?= ""
BBLAYERS ?= " \
    /home/user/poky/meta \
```

(continues on next page)

(continua dalla pagina precedente)

```

/home/user/poky/meta-poky \
/home/user/poky/meta-yocto-bsp \
/home/user/mystuff/meta-mylayer \
"

```

BitBake parses each `conf/layer.conf` file from the top down as specified in the `BBLAYERS` variable within the `build/conf/bblayers.conf` file. During the processing of each `conf/layer.conf` file, BitBake adds the recipes, classes and configurations contained within the particular layer to the source directory.

### 8.3.5 Appending Other Layers Metadata With Your Layer

A recipe that appends Metadata to another recipe is called a BitBake append file. A BitBake append file uses the `.bbappend` file type suffix, while the corresponding recipe to which Metadata is being appended uses the `.bb` file type suffix.

You can use a `.bbappend` file in your layer to make additions or changes to the content of another layer's recipe without having to copy the other layer's recipe into your layer. Your `.bbappend` file resides in your layer, while the main `.bb` recipe file to which you are appending Metadata resides in a different layer.

Being able to append information to an existing recipe not only avoids duplication, but also automatically applies recipe changes from a different layer into your layer. If you were copying recipes, you would have to manually merge changes as they occur.

When you create an append file, you must use the same root name as the corresponding recipe file. For example, the append file `someapp_3.1.bbappend` must apply to `someapp_3.1.bb`. This means the original recipe and append filenames are version number-specific. If the corresponding recipe is renamed to update to a newer version, you must also rename and possibly update the corresponding `.bbappend` as well.

During the build process, BitBake displays an error on startup if it detects a `.bbappend` file that does not have a corresponding recipe with a matching name. To handle these errors, the best practice is to rename the `.bbappend` to match the original recipe version. This also gives you the opportunity to see if the `.bbappend` is still relevant for the new version of the recipe.

Another method is to use the character `%` in the `.bbappend` filename. For example, to append information to every `6.*` minor versions of the recipe `someapp`, the `someapp_6.%bbappend` file can be created. This way, an error will only be triggered if the `someapp` recipe has a major version update.

Finally, another method to deal with these errors is to use the variable `BBMASK`, especially in cases where modifying the `.bbappend` is not possible.

### Overlaying a File Using Your Layer

As an example, consider the main `formfactor` recipe and a corresponding `formfactor` append file both from *OpenEmbedded-Core (OE-Core)*. Here is the main `formfactor` recipe, which is named `formfactor_0.0.bb` and located in the "meta" layer at `meta/recipes-bsp/formfactor`:

```

SUMMARY = "Device formfactor information"
DESCRIPTION = "A formfactor configuration file provides information about the \

```

(continues on next page)

(continua dalla pagina precedente)

```

target hardware for which the image is being built and information that the \
build system cannot obtain from other sources such as the kernel."
SECTION = "base"
LICENSE = "MIT"
LIC_FILES_CHKSUM = "file://${COREBASE}/meta/COPYING.MIT;
↪md5=3da9cfbcb788c80a0384361b4de20420"

SRC_URI = "file://config file://machconfig"
S = "${UNPACKDIR}"

PACKAGE_ARCH = "${MACHINE_ARCH}"
INHIBIT_DEFAULT_DEPS = "1"

do_install() {
    # Install file only if it has contents
    install -d ${D}${sysconfdir}/formfactor/
    install -m 0644 ${S}/config ${D}${sysconfdir}/formfactor/
    if [ -s "${S}/machconfig" ]; then
        install -m 0644 ${S}/machconfig ${D}${sysconfdir}/formfactor/
    fi
}

```

In the main recipe, note the *SRC\_URI* variable, which tells the OpenEmbedded build system where to find files during the build.

Here is the append file, which is named `formfactor_0.0.bbappend` and is from the Raspberry Pi BSP Layer named `meta-raspberrypi`. The file is in the layer at `recipes-bsp/formfactor`:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"
```

By default, the build system uses the *FILESPATH* variable to locate files. This append file extends the locations by setting the *FILESEXTRAPATHS* variable. Setting this variable in the `.bbappend` file is the most reliable and recommended method for adding directories to the search path used by the build system to find files.

The statement in this example extends the directories to include `${THISDIR}/${PN}`, which resolves to a directory named `formfactor` in the same directory in which the append file resides (i.e. `meta-raspberrypi/recipes-bsp/formfactor`). This implies that you must have the supporting directory structure set up that will contain any files or patches you will be including from the layer.

Using the immediate expansion assignment operator `:=` is important because of the reference to *THISDIR*. The trailing colon character is important as it ensures that items in the list remain colon-separated.

### Nota

BitBake automatically defines the *THISDIR* variable. You should never set this variable yourself. Using `":prepend"` as part of the *FILESEXTRAPATHS* ensures your path will be searched prior to other paths in the final list.

Also, not all append files add extra files. Many append files simply allow to add build options (e.g. `systemd`). For these cases, your append file would not even use the `FILESEXTRAPATHS` statement.

The end result of this `.bbappend` file is that on a Raspberry Pi, where `rpi` will exist in the list of `FILESOVERRIDES`, the file `meta-raspberrypi/recipes-bsp/formfactor/formfactor/rpi/machconfig` will be used during `do_fetch` and the test for a non-zero file size in `do_install` will return true, and the file will be installed.

### Installing Additional Files Using Your Layer

As another example, consider the main `xserver-xf86-config` recipe and a corresponding `xserver-xf86-config` append file both from *OpenEmbedded-Core (OE-Core)*. Here is the main `xserver-xf86-config` recipe, which is named `xserver-xf86-config_0.1.bb` and located in the "meta" layer at `meta/recipes-graphics/xorg-xserver`:

```
SUMMARY = "X.Org X server configuration file"
HOMEPAGE = "http://www.x.org"
SECTION = "x11/base"
LICENSE = "MIT"
LIC_FILES_CHKSUM = "file://${COREBASE}/meta/COPYING.MIT;
→md5=3da9cfbcb788c80a0384361b4de20420"

SRC_URI = "file://xorg.conf"

S = "${UNPACKDIR}"

CONFFILES:${PN} = "${sysconfdir}/X11/xorg.conf"

PACKAGE_ARCH = "${MACHINE_ARCH}"
ALLOW_EMPTY:${PN} = "1"

do_install () {
    if test -s ${UNPACKDIR}/xorg.conf; then
        install -d ${D}/${sysconfdir}/X11
        install -m 0644 ${UNPACKDIR}/xorg.conf ${D}/${sysconfdir}/X11/
    fi
}
```

Here is the append file, which is named `xserver-xf86-config_%.bbappend` and is from the Raspberry Pi BSP Layer named `meta-raspberrypi`. The file is in the layer at `recipes-graphics/xorg-xserver`:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"

SRC_URI:append:rpi = " \
    file://xorg.conf.d/98-pitft.conf \
    file://xorg.conf.d/99-calibration.conf \
```

(continues on next page)

(continua dalla pagina precedente)

```

"
do_install:append:rpi () {
    PITFT = "${@bb.utils.contains("MACHINE_FEATURES", "pitft", "1", "0", d)}"
    if [ "${PITFT}" = "1" ]; then
        install -d ${D}/${sysconfdir}/X11/xorg.conf.d/
        install -m 0644 ${UNPACKDIR}/xorg.conf.d/98-pitft.conf ${D}/${sysconfdir}/
↪X11/xorg.conf.d/
        install -m 0644 ${UNPACKDIR}/xorg.conf.d/99-calibration.conf ${D}/${
↪sysconfdir}/X11/xorg.conf.d/
    fi
}

FILES:${PN}:append:rpi = " ${sysconfdir}/X11/xorg.conf.d/*"

```

Building off of the previous example, we once again are setting the *FILESEXTRAPATHS* variable. In this case we are also using *SRC\_URI* to list additional source files to use when *rpi* is found in the list of *FILESOVERRIDES*. The *do\_install* task will then perform a check for an additional *MACHINE\_FEATURES* that if set will cause these additional files to be installed. These additional files are listed in *FILES* so that they will be packaged.

### 8.3.6 Prioritizing Your Layer

Each layer is assigned a priority value. Priority values control which layer takes precedence if there are recipe files with the same name in multiple layers. For these cases, the recipe file from the layer with a higher priority number takes precedence. Priority values also affect the order in which multiple *.bbappend* files for the same recipe are applied. You can either specify the priority manually, or allow the build system to calculate it based on the layer's dependencies.

To specify the layer's priority manually, use the *BBFILE\_PRIORITY* variable and append the layer's root name:

```
BBFILE_PRIORITY_mylayer = "1"
```

#### Nota

It is possible for a recipe with a lower version number *PV* in a layer that has a higher priority to take precedence. Also, the layer priority does not currently affect the precedence order of *.conf* or *.bbclass* files. Future versions of BitBake might address this.

### Providing Global-level Configurations With Your Layer

When creating a layer, you may need to define configurations that should take effect globally in your build environment when the layer is part of the build. The *layer.conf* file is a *configuration file* that affects the build system globally, so it is a candidate for this use-case.



**⚠ Avvertimento**

Providing unconditional global level configuration from the `layer.conf` file is *not* a good practice, and should be avoided. For this reason, the section *Conditionally Provide Global-level Configurations With Your Layer* below shows how the `layer.conf` file can be used to provide configurations only if a certain condition is met.

For example, if your layer provides a Linux kernel recipe named `linux-custom`, you may want to make `PREFERRED_PROVIDER_virtual/kernel` point to `linux-custom`:

```
PREFERRED_PROVIDER_virtual/kernel = "linux-custom"
```

This can be defined in the `layer.conf` file. If your layer is at the last position in the `BBLAYERS` list, it will take precedence over previous `PREFERRED_PROVIDER_virtual/kernel` assignments (unless one is set from a *configuration file* that is parsed later, such as machine or distro configuration files).

### Conditionally Provide Global-level Configurations With Your Layer

In some cases, your layer may provide global configurations only if some features it provides are enabled. Since the `layer.conf` file is parsed at an earlier stage in the parsing process, the `DISTRO_FEATURES` and `MACHINE_FEATURES` variables are not yet available to `layer.conf`, and declaring conditional assignments based on these variables is not possible. The following technique shows a way to bypass this limitation by using the `USER_CLASSES` variable and a conditional `require` command.

In the following steps, let's assume our layer is named `meta-mylayer` and that this layer defines a custom *distro feature* named `mylayer-kernel`. We will set the `PREFERRED_PROVIDER` variable for the kernel only if our feature `mylayer-kernel` is part of the `DISTRO_FEATURES`:

1. Create an include file in the directory `meta-mylayer/conf/distro/include/`, for example a file named `mylayer-kernel-provider.inc` that sets the kernel provider to `linux-custom`:

```
PREFERRED_PROVIDER_virtual/kernel = "linux-custom"
```

2. Provide a path to this include file in your `layer.conf`:

```
META_MYLAYER_KERNEL_PROVIDER_PATH = "${LAYERDIR}/conf/distro/include/mylayer-  
→kernel-provider.inc"
```

3. Create a new class in `meta-mylayer/classes-global/`, for example a class `meta-mylayer-cfg.bbclass`. Make it conditionally require the file `mylayer-kernel-provider.inc` defined above, using the variable `META_MYLAYER_KERNEL_PROVIDER_PATH` defined in `layer.conf`:

```
require ${@bb.utils.contains('DISTRO_FEATURES', 'mylayer-kernel', '${META_  
→MYLAYER_KERNEL_PROVIDER_PATH}', '', d)}
```

For details on the `bb.utils.contains` function, see its definition in `lib/bb/utils.py`.

**i Nota**

The `require` command is designed to not fail if the function `bb.utils.contains` returns an empty string.

4. Back to your `layer.conf` file, add the class `meta-mylayer-cfg` class to the `USER_CLASSES` variable:

```
USER_CLASSES:append = " meta-mylayer-cfg"
```

This will add the class `meta-mylayer-cfg` to the list of classes to globally inherit. Since the `require` command is conditional in `meta-mylayer-cfg.bbclass`, even though inherited the class will have no effect unless the feature `mylayer-kernel` is enabled through `DISTRO_FEATURES`.

This technique can also be used for *Machine features* by following the same steps. Though not mandatory, it is recommended to put include files for `DISTRO_FEATURES` in your layer's `conf/distro/include` and the ones for `MACHINE_FEATURES` in your layer's `conf/machine/include`.

### 8.3.7 Managing Layers

You can use the BitBake layer management tool `bitbake-layers` to provide a view into the structure of recipes across a multi-layer project. Being able to generate output that reports on configured layers with their paths and priorities and on `.bbappend` files and their applicable recipes can help to reveal potential problems.

For help on the BitBake layer management tool, use the following command:

```
$ bitbake-layers --help
```

The following list describes the available commands:

- `help`: Displays general help or help on a specified command.
- `show-layers`: Shows the current configured layers.
- `show-overlaid`: Lists overlaid recipes. A recipe is overlaid when a recipe with the same name exists in another layer that has a higher layer priority.
- `show-recipes`: Lists available recipes and the layers that provide them.
- `show-appends`: Lists `.bbappend` files and the recipe files to which they apply.
- `show-cross-depends`: Lists dependency relationships between recipes that cross layer boundaries.
- `add-layer`: Adds a layer to `build/conf/bblayers.conf`.
- `remove-layer`: Removes a layer from `build/conf/bblayers.conf`.
- `flatten`: Flattens the layer configuration into a separate output directory. Flattening your layer configuration builds a "flattened" directory that contains the contents of all layers, with any overlaid recipes removed and any `.bbappend` files appended to the corresponding recipes. You might have to perform some manual cleanup of the flattened layer as follows:
  - Non-recipe files (such as patches) are overwritten. The `flatten` command shows a warning for these files.

- Anything beyond the normal layer setup has been added to the `layer.conf` file. Only the lowest priority layer's `layer.conf` is used.
- Overridden and appended items from `.bbappend` files need to be cleaned up. The contents of each `.bbappend` end up in the flattened recipe. However, if there are appended or changed variable values, you need to tidy these up yourself. Consider the following example. Here, the `bitbake-layers` command adds the line `#### bbappended ...` so that you know where the following lines originate:

```
...
DESCRIPTION = "A useful utility"
...
EXTRA_OECONF = "--enable-something"
...

#### bbappended from meta-anotherlayer ####

DESCRIPTION = "Customized utility"
EXTRA_OECONF += "--enable-somethingelse"
```

Ideally, you would tidy up these utilities as follows:

```
...
DESCRIPTION = "Customized utility"
...
EXTRA_OECONF = "--enable-something --enable-somethingelse"
...
```

- `layerindex-fetch`: Fetches a layer from a layer index, along with its dependent layers, and adds the layers to the `build/conf/bblayers.conf` file.
- `layerindex-show-depends`: Finds layer dependencies from the layer index.
- `save-build-conf`: Saves the currently active build configuration (`build/conf/local.conf`, `build/conf/bblayers.conf`) as a template into a layer. This template can later be used for setting up builds via `TEMPLATECONF`. For information about saving and using configuration templates, see "[Creating a Custom Template Configuration Directory](#)".
- `create-layer`: Creates a basic layer.
- `create-layers-setup`: Writes out a configuration file and/or a script that can replicate the directory structure and revisions of the layers in a current build. For more information, see "[Saving and restoring the layers setup](#)".
- `show-machines`: Lists the machines available in the currently configured layers.

### 8.3.8 Aggiungere un Layer Utilizzando lo Script `bitbake-layers`

Once you create your general layer, you must add it to your `build/conf/bblayers.conf` file. Adding the layer to this configuration file makes the OpenEmbedded build system aware of your layer so that it can search it for metadata.

Add your layer by using the `bitbake-layers add-layer` command:

```
$ bitbake-layers add-layer your_layer_name
```

Here is an example that adds a layer named `meta-scottrif` to the configuration file. Following the command that adds the layer is another `bitbake-layers` command that shows the layers that are in your `build/conf/bblayers.conf` file:

```
$ bitbake-layers add-layer meta-scottrif
NOTE: Starting bitbake server...
Parsing recipes: 100% |#####|
↳Time: 0:00:49
Parsing of 1441 .bb files complete (0 cached, 1441 parsed). 2055 targets, 56↳
↳skipped, 0 masked, 0 errors.
$ bitbake-layers show-layers
NOTE: Starting bitbake server...
layer                path
↳ priority
=====
meta                  /home/scottrif/bitbake-builds/layers/openembedded-core/meta ↳
↳                    5
meta-poky             /home/scottrif/bitbake-builds/layers/meta-yocto/meta-poky ↳
↳                    5
meta-yocto-bsp        /home/scottrif/bitbake-builds/layers/meta-yocto/meta-yocto-↳
↳bsp                5
workspace            /home/scottrif/bitbake-builds/build/workspace ↳
↳                    99
meta-scottrif         /home/scottrif/bitbake-builds/build/meta-scottrif ↳
↳                    6
```

Adding the layer to this file enables the build system to locate the layer during the build.

**i Nota**

During a build, the OpenEmbedded build system looks in the layers from the top of the list down to the bottom in that order.

### 8.3.9 Saving and restoring the layers setup

Once you have a working build with the correct set of layers, it is beneficial to capture the layer setup --- what they are, which repositories they come from and which SCM revisions they're at --- into a configuration file, so that this setup can be easily replicated later, perhaps on a different machine. Here's how to do this:

```
$ bitbake-layers create-layers-setup /srv/work/alex/meta-alex/
NOTE: Starting bitbake server...
NOTE: Created /srv/work/alex/meta-alex/setup-layers.json
NOTE: Created /srv/work/alex/meta-alex/setup-layers
```

The tool needs a single argument which tells where to place the output, consisting of a json formatted layer configuration, and a `setup-layers` script that can use that configuration to restore the layers in a different location, or on a different host machine. The argument can point to a custom layer (which is then deemed a "bootstrap" layer that needs to be checked out first), or into a completely independent location.

The replication of the layers is performed by running the `setup-layers` script provided above:

1. Clone the bootstrap layer or some other repository to obtain the json config and the setup script that can use it.
2. Run the script directly with no options:

```
alex@Zen2:/srv/work/alex/my-build$ meta-alex/setup-layers
Note: not checking out source meta-alex, use --force-bootstrap-layer-checkout
↳to override.

Setting up source meta-intel, revision 15.0-hardknott-3.3-310-g0a96edae,
↳branch master
Running 'git init -q /srv/work/alex/my-build/meta-intel'
Running 'git remote remove origin > /dev/null 2>&1; git remote add origin
↳https://git.yoctoproject.org/meta-intel' in /srv/work/alex/my-build/meta-
↳intel
Running 'git fetch -q origin || true' in /srv/work/alex/my-build/meta-intel
Running 'git checkout -q 0a96edae609a3f48befac36af82cf1eed6786b4a' in /srv/
↳work/alex/my-build/meta-intel

Setting up source poky, revision 4.1_M1-372-g55483d28f2, branch akanavin/setup-
↳layers
Running 'git init -q /srv/work/alex/my-build/poky'
Running 'git remote remove origin > /dev/null 2>&1; git remote add origin
↳https://git.yoctoproject.org/poky' in /srv/work/alex/my-build/poky
Running 'git fetch -q origin || true' in /srv/work/alex/my-build/poky
```

(continues on next page)

(continua dalla pagina precedente)

```
Running 'git remote remove poky-contrib > /dev/null 2>&1; git remote add poky-
↳ contrib ssh://git@push.yoctoproject.org/poky-contrib' in /srv/work/alex/my-
↳ build/poky
Running 'git fetch -q poky-contrib || true' in /srv/work/alex/my-build/poky
Running 'git checkout -q 11db0390b02acac1324e0f827beb0e2e3d0d1d63' in /srv/
↳ work/alex/my-build/poky
```

**i Nota**

This will work to update an existing checkout as well.

**i Nota**

The script is self-sufficient and requires only python3 and git on the build machine.

**i Nota**

Both the `create-layers-setup` and the `setup-layers` provided several additional options that customize their behavior - you are welcome to study them via `--help` command line parameter.

## 8.4 Customizing Images

You can customize images to satisfy particular requirements. This section describes several methods and provides guidelines for each.

### 8.4.1 Customizing Images Using `local.conf`

Probably the easiest way to customize an image is to add a package by way of the `build/conf/local.conf` configuration file. Because it is limited to local use, this method generally only allows you to add packages and is not as flexible as creating your own customized image. When you add packages using local variables this way, you need to realize that these variable changes are in effect for every build and consequently affect all images, which might not be what you require.

To add a package to your image using the local configuration file, use the `IMAGE_INSTALL` variable with the `:append` operator:

```
IMAGE_INSTALL:append = " strace"
```

Use of the syntax is important; specifically, the leading space after the opening quote and before the package name, which is `strace` in this example. This space is required since the `:append` operator does not add the space.

Furthermore, you must use `:append` instead of the `+=` operator if you want to avoid ordering issues. The reason for this is because doing so unconditionally appends to the variable and avoids ordering problems due to the variable

being set in image recipes and `.bbclass` files with operators like `?.` Using `:append` ensures the operation takes effect.

As shown in its simplest use, `IMAGE_INSTALL:append` affects all images. It is possible to extend the syntax so that the variable applies to a specific image only. Here is an example:

```
IMAGE_INSTALL:append:pn-core-image-minimal = " strace"
```

This example adds `strace` to the `core-image-minimal` image only.

You can add packages using a similar approach through the `CORE_IMAGE_EXTRA_INSTALL` variable. If you use this variable, only `core-image-*` images are affected.

#### 8.4.2 Customizing Images Using Custom `IMAGE_FEATURES` and `EXTRA_IMAGE_FEATURES`

Another method for customizing your image is to enable or disable high-level image features by using the `IMAGE_FEATURES` and `EXTRA_IMAGE_FEATURES` variables. Although the functions for both variables are nearly equivalent, best practices dictate using `IMAGE_FEATURES` from within a recipe and using `EXTRA_IMAGE_FEATURES` from within your `build/conf/local.conf` for temporary changes (which is found in the *Build Directory*) and a distro *configuration file* for permanent changes.

To understand how these features work, the best reference is *meta/classes-recipe/image.bbclass*. This class lists out the available `IMAGE_FEATURES` of which most map to package groups while some, such as `read-only-rootfs`, resolve as general configuration settings.

In summary, the file looks at the contents of the `IMAGE_FEATURES` variable and then maps or configures the feature accordingly. Based on this information, the build system automatically adds the appropriate packages or configurations to the `IMAGE_INSTALL` variable. Effectively, you are enabling extra features by extending the class or creating a custom class for use with specialized image `.bb` files.

Use the `EXTRA_IMAGE_FEATURES` variable from within your local configuration file. Using a separate area from which to enable features with this variable helps you avoid overwriting the features in the image recipe that are enabled with `IMAGE_FEATURES`. The value of `EXTRA_IMAGE_FEATURES` is added to `IMAGE_FEATURES` within `meta/conf/bitbake.conf`.

To illustrate how you can use these variables to modify your image, consider an example that selects the SSH server. The Yocto Project ships with two SSH servers you can use with your images: Dropbear and OpenSSH. Dropbear is a minimal SSH server appropriate for resource-constrained environments, while OpenSSH is a well-known standard SSH server implementation. By default, the `core-image-sato` image is configured to use Dropbear. The `core-image-full-cmdline` image includes OpenSSH. The `core-image-minimal` image does not contain an SSH server.

You can customize your image and change these defaults. Edit the `IMAGE_FEATURES` variable in your recipe or use the `EXTRA_IMAGE_FEATURES` in your `build/conf/local.conf` file (or distro *configuration file*) so that it configures the image you are working with to include `ssh-server-dropbear` or `ssh-server-openssh`.

**i Nota**

See the "*Image Features*" section in the Yocto Project Reference Manual for a complete list of image features that ship with the Yocto Project.

### 8.4.3 Customizing Images Using Custom .bb Files

You can also customize an image by creating a custom recipe that defines additional software as part of the image. The following example shows the form for the two lines you need:

```
IMAGE_INSTALL = "packagegroup-core-x11-base package1 package2"
inherit core-image
```

Defining the software using a custom recipe gives you total control over the contents of the image. It is important to use the correct names of packages in the *IMAGE\_INSTALL* variable. You must use the OpenEmbedded notation and not the Debian notation for the names (e.g. *glibc-dev* instead of *libc6-dev*).

The other method for creating a custom image is to base it on an existing image. For example, if you want to create an image based on *core-image-sato* but add the additional package *strace* to the image, copy the *meta/recipes-sato/images/core-image-sato.bb* to a new *.bb* and add the following line to the end of the copy:

```
IMAGE_INSTALL += "strace"
```

### 8.4.4 Customizing Images Using Custom Package Groups

For complex custom images, the best approach for customizing an image is to create a custom package group recipe that is used to build the image or images. A good example of a package group recipe is *meta/recipes-core/packagegroups/packagegroup-base.bb*.

If you examine that recipe, you see that the *PACKAGES* variable lists the package group packages to produce. The *inherit packagegroup* statement sets appropriate default values and automatically adds *-dev*, *-dbg*, and *-ptest* complementary packages for each package specified in the *PACKAGES* statement.

**i Nota**

The *inherit packagegroup* line should be located near the top of the recipe, certainly before the *PACKAGES* statement.

For each package you specify in *PACKAGES*, you can use *RDEPENDS* and *RRECOMMENDS* entries to provide a list of packages the parent task package should contain. You can see examples of these further down in the *packagegroup-base.bb* recipe.

Here is a short, fabricated example showing the same basic pieces for a hypothetical packagegroup defined in *packagegroup-custom.bb*, where the variable *PN* is the standard way to abbreviate the reference to the full packagegroup name *packagegroup-custom*:



```
DESCRIPTION = "My Custom Package Groups"
```

```
inherit packagegroup
```

```
PACKAGES = "\
    ${PN}-apps \
    ${PN}-tools \
    "
```

```
RDEPENDS:${PN}-apps = "\
    dropbear \
    portmap \
    psplash"
```

```
RDEPENDS:${PN}-tools = "\
    oprofile \
    oprofileui-server \
    lttng-tools"
```

```
RRECOMMENDS:${PN}-tools = "\
    kernel-module-oprofile"
```

In the previous example, two package group packages are created with their dependencies and their recommended package dependencies listed: `packagegroup-custom-apps`, and `packagegroup-custom-tools`. To build an image using these package group packages, you need to add `packagegroup-custom-apps` and/or `packagegroup-custom-tools` to *IMAGE\_INSTALL*. For other forms of image dependencies see the other areas of this section.

### 8.4.5 Customizing an Image Hostname

By default, the configured hostname (i.e. `/etc/hostname`) in an image is the same as the machine name. For example, if *MACHINE* equals "qemux86", the configured hostname written to `/etc/hostname` is "qemux86".

You can customize this name by altering the value of the "hostname" variable in the `base-files` recipe using either an append file or a configuration file. Use the following in an append file:

```
hostname = "myhostname"
```

Use the following in a configuration file:

```
hostname:pn-base-files = "myhostname"
```

Changing the default value of the variable "hostname" can be useful in certain situations. For example, suppose you need to do extensive testing on an image and you would like to easily identify the image under test from existing images with typical default hostnames. In this situation, you could change the default hostname to "testme", which

results in all the images using the name "testme". Once testing is complete and you do not need to rebuild the image for test any longer, you can easily reset the default hostname.

Another point of interest is that if you unset the variable, the image will have no default hostname in the filesystem. Here is an example that unsets the variable in a configuration file:

```
hostname:pn-base-files = ""
```

Having no default hostname in the filesystem is suitable for environments that use dynamic hostnames such as virtual machines.

## 8.5 Scrivere una Nuova Ricetta


Recipes (`.bb` files) are fundamental components in the Yocto Project environment. Each software component built by the OpenEmbedded build system requires a recipe to define the component. This section describes how to create, write, and test a new recipe.

### Nota

For information on variables that are useful for recipes and for information about recipe naming issues, see the "*Ricette*" section of the Yocto Project Reference Manual.

### 8.5.1 Overview

The following figure shows the basic process for creating a new recipe. The remainder of the section provides details for the steps.



## 8.5.2 Locate or Automatically Create a Base Recipe

You can always write a recipe from scratch. However, there are three choices that can help you quickly get started with a new recipe:

- `devtool add`: A command that assists in creating a recipe and an environment conducive to development.
- `recipetool create`: A command provided by the Yocto Project that automates creation of a base recipe based on the source files.
- *Existing Recipes*: Location and modification of an existing recipe that is similar in function to the recipe you need.

**i Nota**

For information on recipe syntax, see the "*Recipe Syntax*" section.

### Creating the Base Recipe Using `devtool add`

The `devtool add` command uses the same logic for auto-creating the recipe as `recipetool create`, which is listed below. Additionally, however, `devtool add` sets up an environment that makes it easy for you to patch the source and to make changes to the recipe as is often necessary when adding a recipe to build a new piece of software to be included in a build.

You can find a complete description of the `devtool add` command in the "*A Closer Look at devtool add*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.

### Creating the Base Recipe Using `recipetool create`

`recipetool create` automates creation of a base recipe given a set of source code files. As long as you can extract or point to the source files, the tool will construct a recipe and automatically configure all pre-build information into the recipe. For example, suppose you have an application that builds using Autotools. Creating the base recipe using `recipetool` results in a recipe that has the pre-build dependencies, license requirements, and checksums configured.

To run the tool, you just need to be in your *Build Directory* and have sourced the build environment setup script (i.e. *oe-init-build-env*). To get help on the tool, use the following command:

```
$ recipetool -h
NOTE: Starting bitbake server...
usage: recipetool [-d] [-q] [--color COLOR] [-h] <subcommand> ...

OpenEmbedded recipe tool

options:
  -d, --debug           Enable debug output
  -q, --quiet           Print only errors
  --color COLOR         Colorize output (where COLOR is auto, always, never)
  -h, --help           show this help message and exit

subcommands:
  newappend             Create a bbappend for the specified target in the specified
↳ layer
  create                Create a new recipe
  setvar               Set a variable within a recipe
  appendfile           Create/update a bbappend to replace a target file
  appendsrcfiles       Create/update a bbappend to add or replace source files
  appendsrcfile        Create/update a bbappend to add or replace a source file
  edit                 Edit the recipe and appends for the specified target. This
↳ obeys $VISUAL if set,
```

(continues on next page)

(continua dalla pagina precedente)

```
otherwise $EDITOR, otherwise vi.
```

```
Use recipetool <subcommand> --help to get help on a specific command
```

Running `recipetool create -o OUTFILE` creates the base recipe and locates it properly in the layer that contains your source files. Here are some syntax examples:

- Use this syntax to generate a recipe based on source. Once generated, the recipe resides in the existing source code layer:

```
recipetool create -o OUTFILE source
```

- Use this syntax to generate a recipe using code that you extract from source. The extracted code is placed in its own layer defined by [EXTERNALSRC](#):

```
recipetool create -o OUTFILE -x EXTERNALSRC source
```

- Use this syntax to generate a recipe based on source. The options direct `recipetool` to generate debugging information. Once generated, the recipe resides in the existing source code layer:

```
recipetool create -d -o OUTFILE source
```

## Locating and Using a Similar Recipe

Before writing a recipe from scratch, it is often useful to discover whether someone else has already written one that meets (or comes close to meeting) your needs. The Yocto Project and OpenEmbedded communities maintain many recipes that might be candidates for what you are doing. You can find a good central index of these recipes in the [OpenEmbedded Layer Index](#).

Working from an existing recipe or a skeleton recipe is the best way to get started. Here are some points on both methods:

- *Locate and modify a recipe that is close to what you want to do:* This method works when you are familiar with the current recipe space. The method does not work so well for those new to the Yocto Project or writing recipes.

Some risks associated with this method are using a recipe that has areas totally unrelated to what you are trying to accomplish with your recipe, not recognizing areas of the recipe that you might have to add from scratch, and so forth. All these risks stem from unfamiliarity with the existing recipe space.

- *Use and modify the following skeleton recipe:* If for some reason you do not want to use `recipetool` and you cannot find an existing recipe that is close to meeting your needs, you can use the following structure to provide the fundamental areas of a new recipe:

```
DESCRIPTION = ""
HOMEPAGE = ""
LICENSE = ""
SECTION = ""
DEPENDS = ""
```

(continues on next page)

(continua dalla pagina precedente)

```
LIC_FILES_CHKSUM = ""

SRC_URI = ""
```

### 8.5.3 Storing and Naming the Recipe

Once you have your base recipe, you should put it in your own layer and name it appropriately. Locating it correctly ensures that the OpenEmbedded build system can find it when you use BitBake to process the recipe.

- *Storing Your Recipe:* The OpenEmbedded build system locates your recipe through the layer's `conf/layer.conf` file and the `BBFILES` variable. This variable sets up a path from which the build system can locate recipes. Here is the typical use:

```
BBFILES += "${LAYERDIR}/recipes-*/*/*.bb \
           ${LAYERDIR}/recipes-*/*/*.bbappend"
```

Consequently, you need to be sure you locate your new recipe inside your layer such that it can be found.

You can find more information on how layers are structured in the "*Comprendere e Creare i Layer*" section.

- *Naming Your Recipe:* When you name your recipe, you need to follow this naming convention:

```
basename_version.bb
```

Use lower-cased characters and do not include the reserved suffixes `-native`, `-cross`, `-initial`, or `-dev` casually (i.e. do not use them as part of your recipe name unless the string applies). Here are some examples (which includes the use of the string "git" as a special case of a version identifier):

```
cups_2.4.12.bb
gawk_5.3.2.bb
psplash_git.bb
```

### 8.5.4 Running a Build on the Recipe

Creating a new recipe is usually an iterative process that requires using BitBake to process the recipe multiple times in order to progressively discover and add information to the recipe file.

Assuming you have sourced the build environment setup script (i.e. `oe-init-build-env`) and you are in the *Build Directory*, use BitBake to process your recipe. All you need to provide is the `basename` of the recipe as described in the previous section:

```
$ bitbake basename
```

During the build, the OpenEmbedded build system creates a temporary work directory for each recipe (`${WORKDIR}`) where it keeps extracted source files, log files, intermediate compilation and packaging files, and so forth.

The path to the per-recipe temporary work directory depends on the context in which it is being built. The quickest way to find this path is to use the `bitbake-getvar` utility:

```
$ bitbake-getvar -r basename WORKDIR
```

As an example, assume a *Source Directory* top-level folder named `bitbake-builds`, a default *Build Directory* at `bitbake-builds/build`, a `cortexa57` *PACKAGE\_ARCH*, `poky` *DISTRO* and `linux` as *TARGET\_OS*.

Furthermore, suppose your recipe is named `foo_1.3.0.bb`. In this case, the work directory the build system uses to build the package would be as follows:

```
bitbake-builds/build/tmp/work/cortexa57-poky-linux/foo/1.3.0
```

#### Nota

This covers the case when the *PACKAGE\_ARCH* variable is set to its default value, *TUNE\_PKGARCH*. This variable is sometimes set to *MACHINE\_ARCH*. See the documentation of the *PACKAGE\_ARCH* variable for more information.

Inside this directory you can find sub-directories such as `image`, `packages-split`, and `temp`. After the build, you can examine these to determine how well the build went.

#### Nota

You can find log files for each task in the recipe's `temp` directory (e.g. `bitbake-builds/build/tmp/work/cortexa57-poky-linux/foo/1.3.0/temp`). Log files are named `log.taskname` (e.g. `log.do_configure`, `log.do_fetch`, and `log.do_compile`).

You can find more information about the build process in "*L'Ambiente di Sviluppo di Yocto Project*" chapter of the Yocto Project Overview and Concepts Manual.

## 8.5.5 Fetching Code

The first thing your recipe must do is specify how to fetch the source files. Fetching is controlled mainly through the *SRC\_URI* variable. Your recipe must have a *SRC\_URI* variable that points to where the source is located. For a graphical representation of source locations, see the "*Sorgenti*" section in the Yocto Project Overview and Concepts Manual.

The *do\_fetch* task uses the prefix of each entry in the *SRC\_URI* variable value to determine which *fetcher* to use to get your source files. It is the *SRC\_URI* variable that triggers the fetcher. The *do\_patch* task uses the variable after source is fetched to apply patches. The OpenEmbedded build system uses *FILESOVERRIDES* for scanning directory locations for local files in *SRC\_URI*.

The *SRC\_URI* variable in your recipe must define each unique location for your source files. It is good practice to not hard-code version numbers in a URL used in *SRC\_URI*. Rather than hard-code these values, use `${PV}`, which causes the fetch process to use the version specified in the recipe filename. Specifying the version in this manner means that upgrading the recipe to a future version is as simple as renaming the recipe to match the new version.

Here is a simple example from the [strace recipe](#) where the source comes from a single tarball. Notice the use of the *PV* variable:

```
SRC_URI = "${GITHUB_BASE_URI}/download/v${PV}/strace-${PV}.tar.xz \
```

Files mentioned in *SRC\_URI* whose names end in a typical archive extension (e.g. .tar, .tar.gz, .tar.bz2, .zip, and so forth), are automatically extracted during the *do\_unpack* task. For another example that specifies these types of files, see the *"Building an Autotooled Package"* section.

Another way of specifying source is from an SCM. For Git repositories, you must specify *SRCREV* and you should specify *PV* to include a + sign in its definition. Here is an example from the recipe *l3afpad\_git.bb*:

```
SRC_URI = "git://github.com/stevenhoneyman/l3afpad.git;branch=master;protocol=https
↪"

PV = "0.8.18.1.11+git"

SRCREV = "3cdccdc9505643e50f8208171d9eee5de11a42ff"
```

If your *SRC\_URI* statement includes URLs pointing to individual files fetched from a remote server other than a version control system, BitBake attempts to verify the files against checksums defined in your recipe to ensure they have not been tampered with or otherwise modified since the recipe was written. Multiple checksums are supported: *SRC\_URI[md5sum]*, *SRC\_URI[sha1sum]*, *SRC\_URI[sha256sum]*, *SRC\_URI[sha384sum]* and *SRC\_URI[sha512sum]*, but only *SRC\_URI[sha256sum]* is commonly used.

#### Nota

*SRC\_URI[md5sum]* used to also be commonly used, but it is deprecated and should be replaced by *SRC\_URI[sha256sum]* when updating existing recipes.

If your *SRC\_URI* variable points to more than a single URL (excluding SCM URLs), you need to provide the *sha256* checksum for each URL. For these cases, you provide a name for each URL as part of the *SRC\_URI* and then reference that name in the subsequent checksum statements. Here is an example combining lines from the files *git.inc* and *git\_2.24.1.bb*:

```
SRC_URI = "${KERNELORG_MIRROR}/software/scm/git/git-${PV}.tar.gz;name=tarball \
          ${KERNELORG_MIRROR}/software/scm/git/git-manpages-${PV}.tar.gz;
↪name=manpages"

SRC_URI[tarball.sha256sum] =
↪"ad5334956301c86841eb1e5b1bb20884a6bad89a10a6762c958220c7cf64da02"

SRC_URI[manpages.sha256sum] =
↪"9a7ae3a093bea39770eb96ca3e5b40bfff7af0b9f6123f089d7821d0e5b8e1230"
```

The proper value for the *sha256* checksum might be available together with other signatures on the download page for the upstream source (e.g. md5, sha1, sha256, GPG, and so forth). Because the OpenEmbedded build system typically only deals with *sha256sum*, you should verify all the signatures you find by hand.



If no *SRC\_URI* checksums are specified when you attempt to build the recipe, or you provide an incorrect checksum, the build will produce an error for each missing or incorrect checksum. As part of the error message, the build system provides the checksum string corresponding to the fetched file. Once you have the correct checksums, you can copy and paste them into your recipe and then run the build again to continue.

#### Nota

As mentioned, if the upstream source provides signatures for verifying the downloaded source code, you should verify those manually before setting the checksum values in the recipe and continuing with the build.

This final example is a bit more complicated and is from the *rxvt-unicode* recipe. The example's *SRC\_URI* statement identifies multiple files as the source files for the recipe: a tarball, a patch file, a desktop file, and an icon:

```
SRC_URI = "http://dist.schmorp.de/rxvt-unicode/Attic/rxvt-unicode-${PV}.tar.bz2 \
    file://xwc.patch \
    file://rxvt.desktop \
    file://rxvt.png"
```

When you specify local files using the `file://` URI protocol, the build system fetches files from the local machine. The path is relative to the *FILESPATH* variable and searches specific directories in a certain order: *BP*, *BPN*, and *files*. The directories are assumed to be subdirectories of the directory in which the recipe or append file resides. For another example that specifies these types of files, see the "*building a single .c file package*" section.

The previous example also specifies a patch file. Patch files are files whose names usually end in `.patch` or `.diff` but can end with compressed suffixes such as `diff.gz` and `patch.bz2`, for example. The build system automatically applies patches as described in the "*Patching Code*" section.

## Fetching Code Through Firewalls

Some users are behind firewalls and need to fetch code through a proxy. See the "*FAQ*" chapter for advice.

## Limiting the Number of Parallel Connections

Some users are behind firewalls or use servers where the number of parallel connections is limited. In such cases, you can limit the number of fetch tasks being run in parallel by adding the following to your *build/conf/local.conf* file:

```
do_fetch[number_threads] = "4"
```

## 8.5.6 Unpacking Code

During the build, the *do\_unpack* task unpacks the source with *S* pointing to where it is unpacked.

By default, the value of *S* is already set to where the *OpenEmbedded Build System* will unpack the source code, by using the value of *UNPACKDIR* and *BP*.

You typically don't need to set *S* explicitly. If processing your recipe using BitBake successfully unpacks the source files, you can verify that the directory pointed to by *S* is the root of your source code.

**i Nota**

It used to be that when fetching with Git, recipes should explicitly set *S* to `${WORKDIR}/git`: this is no longer the case. See *S = \${WORKDIR}/git and S = \${UNPACKDIR}/git should be removed* for more information.

### 8.5.7 Patching Code

Sometimes it is necessary to patch code after it has been fetched. Any files mentioned in *SRC\_URI* whose names end in `.patch` or `.diff` or compressed versions of these suffixes (e.g. `diff.gz`, `patch.bz2`, etc.) are treated as patches. The *do\_patch* task automatically applies these patches.

The build system should be able to apply patches with the `-p1` option (i.e. one directory level in the path will be stripped off). If your patch needs to have more directory levels stripped off, specify the number of levels using the `"striplevel"` option in the *SRC\_URI* entry for the patch. Alternatively, if your patch needs to be applied in a specific subdirectory that is not specified in the patch file, use the `"patchdir"` option in the entry.

As with all local files referenced in *SRC\_URI* using `file://`, you should place patch files in a directory next to the recipe either named the same as the base name of the recipe (*BP* and *BPN*) or `"files"`.

### 8.5.8 Licenze

Your recipe needs to define variables related to the license under which the software is distributed. See the *Campi di Licenza della Ricetta* section in the Contributor Guide for details.

### 8.5.9 Dependencies

Most software packages have a short list of other packages that they require, which are called dependencies. These dependencies fall into two main categories: build-time dependencies, which are required when the software is built; and runtime dependencies, which are required to be installed on the target in order for the software to run.

Within a recipe, you specify build-time dependencies using the *DEPENDS* variable. Although there are nuances, items specified in *DEPENDS* should be names of other recipes. It is important that you specify all build-time dependencies explicitly.

Another consideration is that configure scripts might automatically check for optional dependencies and enable corresponding functionality if those dependencies are found. If you wish to make a recipe that is more generally useful (e.g. publish the recipe in a layer for others to use), instead of hard-disabling the functionality, you can use the *PACKAGECONFIG* variable to allow functionality and the corresponding dependencies to be enabled and disabled easily by other users of the recipe.

Similar to build-time dependencies, you specify runtime dependencies through a variable - *RDEPENDS*, which is package-specific. All variables that are package-specific need to have the name of the package added to the end as an override. Since the main package for a recipe has the same name as the recipe, and the recipe's name can be found through the `${PN}` variable, then you specify the dependencies for the main package by setting `RDEPENDS:${PN}`. If the package were named `${PN}-tools`, then you would set `RDEPENDS:${PN}-tools`, and so forth.

Some runtime dependencies will be set automatically at packaging time. These dependencies include any shared library dependencies (i.e. if a package "example" contains "libexample" and another package "mypackage" contains a binary that links to "libexample" then the OpenEmbedded build system will automatically add a runtime dependency

to "mypackage" on "example"). See the "*Dipendenze di Runtime Aggiunte Automaticamente*" section in the Yocto Project Overview and Concepts Manual for further details.

### 8.5.10 Configuring the Recipe

Most software provides some means of setting build-time configuration options before compilation. Typically, setting these options is accomplished by running a configure script with options, or by modifying a build configuration file.

#### Nota

As of Yocto Project Release 1.7, some of the core recipes that package binary configuration scripts now disable the scripts due to the scripts previously requiring error-prone path substitution. The OpenEmbedded build system uses `pkg-config` now, which is much more robust. You can find a list of the `*-config` scripts that are disabled in the "*Binary Configuration Scripts Disabled*" section in the Yocto Project Reference Manual.

A major part of build-time configuration is about checking for build-time dependencies and possibly enabling optional functionality as a result. You need to specify any build-time dependencies for the software you are building in your recipe's `DEPENDS` value, in terms of other recipes that satisfy those dependencies. You can often find build-time or runtime dependencies described in the software's documentation.

The following list provides configuration items of note based on how your software is built:

- *Autotools*: If your source files have a `configure.ac` file, then your software is built using Autotools. If this is the case, you just need to modify the configuration.

When using Autotools, your recipe needs to inherit the `autotools*` class and it does not have to contain a `do_configure` task. However, you might still want to make some adjustments. For example, you can set `EXTRA_OECONF` or `PACKAGECONFIG_CONFARGS` to pass any needed configure options that are specific to the recipe.

- *CMake*: If your source files have a `CMakeLists.txt` file, then your software is built using CMake. If this is the case, you just need to modify the configuration.

When you use CMake, your recipe needs to inherit the `cmake` class and it does not have to contain a `do_configure` task. You can make some adjustments by setting `EXTRA_OECMAKE` to pass any needed configure options that are specific to the recipe.

#### Nota

If you need to install one or more custom CMake toolchain files that are supplied by the application you are building, install the files to `${D}${datadir}/cmake/Modules` during `do_install`.

- *Other*: If your source files do not have a `configure.ac` or `CMakeLists.txt` file, then your software is built using some method other than Autotools or CMake. If this is the case, you normally need to provide a `do_configure` task in your recipe unless, of course, there is nothing to configure.

Even if your software is not being built by Autotools or CMake, you still might not need to deal with any configuration issues. You need to determine if configuration is even a required step. You might need to modify

a Makefile or some configuration file used for the build to specify necessary build options. Or, perhaps you might need to run a provided, custom configure script with the appropriate options.

For the case involving a custom configure script, you would run `./configure --help` and look for the options you need to set.

Once configuration succeeds, it is always good practice to look at the `log.do_configure` file to ensure that the appropriate options have been enabled and no additional build-time dependencies need to be added to `DEPENDS`. For example, if the configure script reports that it found something not mentioned in `DEPENDS`, or that it did not find something that it needed for some desired optional functionality, then you would need to add those to `DEPENDS`. Looking at the log might also reveal items being checked for, enabled, or both that you do not want, or items not being found that are in `DEPENDS`, in which case you would need to look at passing extra options to the configure script as needed. For reference information on configure options specific to the software you are building, you can consult the output of the `./configure --help` command within `${S}` or consult the software's upstream documentation.

### 8.5.11 Using Headers to Interface with Devices

If your recipe builds an application that needs to communicate with some device or needs an API into a custom kernel, you will need to provide appropriate header files. Under no circumstances should you ever modify the existing `meta/recipes-kernel/linux-libc-headers/linux-libc-headers.inc` file. These headers are used to build `libc` and must not be compromised with custom or machine-specific header information. If you customize `libc` through modified headers all other applications that use `libc` thus become affected.

#### Nota

Never copy and customize the `libc` header file (i.e. `meta/recipes-kernel/linux-libc-headers/linux-libc-headers.inc`).

The correct way to interface to a device or custom kernel is to use a separate package that provides the additional headers for the driver or other unique interfaces. When doing so, your application also becomes responsible for creating a dependency on that specific provider.

Consider the following:

- Never modify `linux-libc-headers.inc`. Consider that file to be part of the `libc` system, and not something you use to access the kernel directly. You should access `libc` through specific `libc` calls.
- Applications that must talk directly to devices should either provide necessary headers themselves, or establish a dependency on a special headers package that is specific to that driver.

For example, suppose you want to modify an existing header that adds I/O control or network support. If the modifications are used by a small number programs, providing a unique version of a header is easy and has little impact. When doing so, bear in mind the guidelines in the previous list.

#### Nota

If for some reason your changes need to modify the behavior of the `libc`, and subsequently all other applications on the system, use a `.bbappend` to modify the `linux-kernel-headers.inc` file. However, take care to not make the changes machine specific.

Consider a case where your kernel is older and you need an older `libc` ABI. The headers installed by your recipe should still be a standard mainline kernel, not your own custom one.

When you use custom kernel headers you need to get them from `STAGING_KERNEL_DIR`, which is the directory with kernel headers that are required to build out-of-tree modules. Your recipe will also need the following:

```
do_configure[depends] += "virtual/kernel:do_shared_workdir"
```

## 8.5.12 Compilation

During a build, the `do_compile` task happens after source is fetched, unpacked, and configured. If the recipe passes through `do_compile` successfully, nothing needs to be done.

However, if the compile step fails, you need to diagnose the failure. Here are some common issues that cause failures.

### Nota

For cases where improper paths are detected for configuration files or for when libraries/headers cannot be found, be sure you are using the more robust `pkg-config`. See the note in section "[Configuring the Recipe](#)" for additional information.

- *Parallel build failures:* These failures manifest themselves as intermittent errors, or errors reporting that a file or directory that should be created by some other part of the build process could not be found. This type of failure can occur even if, upon inspection, the file or directory does exist after the build has failed, because that part of the build process happened in the wrong order.

To fix the problem, you need to either satisfy the missing dependency in the Makefile or whatever script produced the Makefile, or (as a workaround) set `PARALLEL_MAKE` to an empty string:

```
PARALLEL_MAKE = ""
```

For information on parallel Makefile issues, see the "[Debugging Parallel Make Races](#)" section.

- *Improper host path usage:* This failure applies to recipes building for the target or "`nativesdk`" only. The failure occurs when the compilation process uses improper headers, libraries, or other files from the host system when cross-compiling for the target.

To fix the problem, examine the `log.do_compile` file to identify the host paths being used (e.g. `/usr/include`, `/usr/lib`, and so forth) and then either add configure options, apply a patch, or do both.

- *Failure to find required libraries/headers:* If a build-time dependency is missing because it has not been declared in `DEPENDS`, or because the dependency exists but the path used by the build process to find the file is incorrect and the configure step did not detect it, the compilation process could fail. For either of these failures, the compilation process notes that files could not be found. In these cases, you need to go back and add additional options to the configure script as well as possibly add additional build-time dependencies to `DEPENDS`.

Occasionally, it is necessary to apply a patch to the source to ensure the correct paths are used. If you need to specify paths to find files staged into the sysroot from other recipes, use the variables that the OpenEmbedded build system provides (e.g. `STAGING_BINDIR`, `STAGING_INCDIR`, `STAGING_DATADIR`, and so forth).

### 8.5.13 Installing

During `do_install`, the task copies the built files along with their hierarchy to locations that would mirror their locations on the target device. The installation process copies files from the `${S}`, `${B}`, and `${UNPACKDIR}` directories to the `${D}` directory to create the structure as it should appear on the target system.

How your software is built affects what you must do to be sure your software is installed correctly. The following list describes what you must do for installation depending on the type of build system used by the software being built:

- *Autotools and CMake*: If the software your recipe is building uses Autotools or CMake, the OpenEmbedded build system understands how to install the software. Consequently, you do not have to have a `do_install` task as part of your recipe. You just need to make sure the install portion of the build completes with no issues. However, if you wish to install additional files not already being installed by `make install`, you should do this using a `do_install:append` function using the `install` command as described in the "Manual" bulleted item later in this list.
- *Other (using `make install`)*: You need to define a `do_install` function in your recipe. The function should call `oe_runmake install` and will likely need to pass in the destination directory as well. How you pass that path is dependent on how the Makefile being run is written (e.g. `DESTDIR=${D}`, `PREFIX=${D}`, `INSTALLROOT=${D}`, and so forth).

For an example recipe using `make install`, see the "*Building a Makefile-Based Package*" section.

- *Manual*: You need to define a `do_install` function in your recipe. The function must first use `install -d` to create the directories under `${D}`. Once the directories exist, your function can use `install` to manually install the built software into the directories.

You can find more information on `install` at [https://www.gnu.org/software/coreutils/manual/html\\_node/install-invocation.html](https://www.gnu.org/software/coreutils/manual/html_node/install-invocation.html).

For the scenarios that do not use Autotools or CMake, you need to track the installation and diagnose and fix any issues until everything installs correctly. You need to look in the default location of `${D}`, which is `${WORKDIR}/image`, to be sure your files have been installed correctly.

#### Nota

- During the installation process, you might need to modify some of the installed files to suit the target layout. For example, you might need to replace hard-coded paths in an initscript with values of variables provided by the build system, such as replacing `/usr/bin/` with `${bindir}`. If you do perform such modifications during `do_install`, be sure to modify the destination file after copying rather than before copying. Modifying after copying ensures that the build system can re-execute `do_install` if needed.
- `oe_runmake install`, which can be run directly or can be run indirectly by the `autotools*` and `cmake` classes, runs `make install` in parallel. Sometimes, a Makefile can have missing dependencies between targets that can result in race conditions. If you experience intermittent failures during `do_install`, you might be able to work around them by disabling parallel Makefile installs by adding the following to the recipe:

```
PARALLEL_MAKEINST = ""
```

See [PARALLEL\\_MAKEINST](#) for additional information.

- If you need to install one or more custom CMake toolchain files that are supplied by the application you are building, install the files to `${D}${datadir}/cmake/Modules` during [do\\_install](#).

### 8.5.14 Enabling System Services

If you want to install a service, which is a process that usually starts on boot and runs in the background, then you must include some additional definitions in your recipe.

If you are adding services and the service initialization script or the service file itself is not installed, you must provide for that installation in your recipe using a `do_install:append` function. If your recipe already has a [do\\_install](#) function, update the function near its end rather than adding an additional `do_install:append` function.

When you create the installation for your services, you need to accomplish what is normally done by `make install`. In other words, make sure your installation arranges the output similar to how it is arranged on the target system.

The OpenEmbedded build system provides support for starting services two different ways:

- *SysVinit*: SysVinit is a system and service manager that manages the init system used to control the very basic functions of your system. The init program is the first program started by the Linux kernel when the system boots. Init then controls the startup, running and shutdown of all other programs.

To enable a service using SysVinit, your recipe needs to inherit the [update-rc.d](#) class. The class helps facilitate safely installing the package on the target.

You will need to set the [INITSCRIPT\\_PACKAGES](#), [INITSCRIPT\\_NAME](#), and [INITSCRIPT\\_PARAMS](#) variables within your recipe.

- *systemd*: System Management Daemon (systemd) was designed to replace SysVinit and to provide enhanced management of services. For more information on systemd, see the systemd homepage at <https://systemd.io/>.

To enable a service using systemd, your recipe needs to inherit the [systemd](#) class. See the `systemd.bbclass` file located in [OpenEmbedded-Core \(OE-Core\)](#) section for more information.

### 8.5.15 Packaging

Successful packaging is a combination of automated processes performed by the OpenEmbedded build system and some specific steps you need to take. The following list describes the process:

- *Splitting Files*: The [do\\_package](#) task splits the files produced by the recipe into logical components. Even software that produces a single binary might still have debug symbols, documentation, and other logical components that should be split out. The [do\\_package](#) task ensures that files are split up and packaged correctly.
- *Running QA Checks*: The [insane](#) class adds a step to the package generation process so that output quality assurance checks are generated by the OpenEmbedded build system. This step performs a range of checks to be sure the build's output is free of common problems that show up during runtime. For information on these checks, see the [insane](#) class and the "[QA Error and Warning Messages](#)" chapter in the Yocto Project Reference Manual.



- *Hand-Checking Your Packages*: After you build your software, you need to be sure your packages are correct. Examine the `${WORKDIR}/packages-split` directory and make sure files are where you expect them to be. If you discover problems, you can set `PACKAGES`, `FILES`, `do_install(:append)`, and so forth as needed.
- *Splitting an Application into Multiple Packages*: If you need to split an application into several packages, see the "*Splitting an Application into Multiple Packages*" section for an example.
- *Installing a Post-Installation Script*: For an example showing how to install a post-installation script, see the "*Post-Installation Scripts*" section.
- *Marking Package Architecture*: Depending on what your recipe is building and how it is configured, it might be important to mark the packages produced as being specific to a particular machine, or to mark them as not being specific to a particular machine or architecture at all.

By default, packages apply to any machine with the same architecture as the target machine. When a recipe produces packages that are machine-specific (e.g. the `MACHINE` value is passed into the configure script or a patch is applied only for a particular machine), you should mark them as such by adding the following to the recipe:

```
PACKAGE_ARCH = "${MACHINE_ARCH}"
```

On the other hand, if the recipe produces packages that do not contain anything specific to the target machine or architecture at all (e.g. recipes that simply package script files or configuration files), you should use the `allarch` class to do this for you by adding this to your recipe:

```
inherit allarch
```

Ensuring that the package architecture is correct is not critical while you are doing the first few builds of your recipe. However, it is important in order to ensure that your recipe rebuilds (or does not rebuild) appropriately in response to changes in configuration, and to ensure that you get the appropriate packages installed on the target machine, particularly if you run separate builds for more than one target machine.

## 8.5.16 Sharing Files Between Recipes

Recipes often need to use files provided by other recipes on the build host. For example, an application linking to a common library needs access to the library itself and its associated headers. The way this access is accomplished is by populating a sysroot with files. Each recipe has two sysroots in its work directory, one for target files (`recipe-sysroot`) and one for files that are native to the build host (`recipe-sysroot-native`).

### Nota

You could find the term "staging" used within the Yocto project regarding files populating sysroots (e.g. the `STAGING_DIR` variable).

Recipes should never populate the sysroot directly (i.e. write files into sysroot). Instead, files should be installed into standard locations during the `do_install` task within the `${D}` directory. The reason for this limitation is that almost



all files that populate the sysroot are cataloged in manifests in order to ensure the files can be removed later when a recipe is either modified or removed. Thus, the sysroot is able to remain free from stale files.

A subset of the files installed by the `do_install` task are used by the `do_populate_sysroot` task as defined by the `SYSROOT_DIRS` variable to automatically populate the sysroot. It is possible to modify the list of directories that populate the sysroot. The following example shows how you could add the `/opt` directory to the list of directories within a recipe:

```
SYSROOT_DIRS += "/opt"
```

#### Nota

The `/sysroot-only` is to be used by recipes that generate artifacts that are not included in the target filesystem, allowing them to share these artifacts without needing to use the `DEPLOY_DIR`.

For a more complete description of the `do_populate_sysroot` task and its associated functions, see the `staging` class.

## 8.5.17 Using Virtual Providers

Prior to a build, if you know that several different recipes provide the same functionality, you can use a virtual provider (i.e. `virtual/*`) as a placeholder for the actual provider. The actual provider is determined at build-time.

A common scenario where a virtual provider is used would be for the kernel recipe. Suppose you have three kernel recipes whose `PN` values map to `kernel-big`, `kernel-mid`, and `kernel-small`. Furthermore, each of these recipes in some way uses a `PROVIDES` statement that essentially identifies itself as being able to provide `virtual/kernel`. Here is one way through the `kernel` class:

```
PROVIDES += "virtual/kernel"
```

Any recipe that inherits the `kernel` class is going to utilize a `PROVIDES` statement that identifies that recipe as being able to provide the `virtual/kernel` item.

Now comes the time to actually build an image and you need a kernel recipe, but which one? You can configure your build to call out the kernel recipe you want by using the `PREFERRED_PROVIDER` variable. As an example, consider the `x86-base.inc` include file, which is a machine (i.e. `MACHINE`) configuration file. This include file is the reason all x86-based machines use the `linux-yocto` kernel. Here is the relevant line from that include file:

```
PREFERRED_PROVIDER_virtual/kernel ??= "linux-yocto"
```

When you use a virtual provider, you do not have to "hard code" a recipe name as a build dependency. You can use the `DEPENDS` variable to state the build is dependent on `virtual/kernel` for example:

```
DEPENDS = "virtual/kernel"
```

During the build, the OpenEmbedded build system picks the correct recipe needed for the `virtual/kernel` dependency based on the `PREFERRED_PROVIDER` variable. If you want to use the small kernel mentioned at the beginning of this section, configure your build as follows:

```
PREFERRED_PROVIDER_virtual/kernel ??= "kernel-small"
```

#### Nota

Any recipe that *PROVIDES* a `virtual/*` item that is ultimately not selected through *PREFERRED\_PROVIDER* does not get built. Preventing these recipes from building is usually the desired behavior since this mechanism's purpose is to select between mutually exclusive alternative providers.

The following lists specific examples of virtual providers:

- `virtual/kernel`: Provides the name of the kernel recipe to use when building a kernel image.
- `virtual/bootloader`: Provides the name of the bootloader to use when building an image.
- `virtual/libgbm`: Provides `gbm.pc`.
- `virtual/egl`: Provides `egl.pc` and possibly `wayland-egl.pc`.
- `virtual/libgl`: Provides `gl.pc` (i.e. libGL).
- `virtual/libgles1`: Provides `glesv1_cm.pc` (i.e. libGLESv1\_CM).
- `virtual/libgles2`: Provides `glesv2.pc` (i.e. libGLESv2).

#### Nota

Virtual providers only apply to build time dependencies specified with *PROVIDES* and *DEPENDS*. They do not apply to runtime dependencies specified with *RPROVIDES* and *RDEPENDS*.

## 8.5.18 Properly Versioning Pre-Release Recipes

Sometimes the name of a recipe can lead to versioning problems when the recipe is upgraded to a final release. For example, consider the `irssi_0.8.16-rc1.bb` recipe file in the list of example recipes in the "*Storing and Naming the Recipe*" section. This recipe is at a release candidate stage (i.e. "rc1"). When the recipe is released, the recipe filename becomes `irssi_0.8.16.bb`. The version change from `0.8.16-rc1` to `0.8.16` is seen as a decrease by the build system and package managers, so the resulting packages will not correctly trigger an upgrade.

In order to ensure the versions compare properly, the recommended convention is to use a tilde (~) character as follows:

```
PV = "0.8.16~rc1"
```

This way `0.8.16~rc1` sorts before `0.8.16`. See the "*Politica sulle Versioni*" section in the Yocto Project and OpenEmbedded Contributor Guide for more details about versioning code corresponding to a pre-release or to a specific Git commit.

## 8.5.19 Post-Installation Scripts

Post-installation scripts run immediately after installing a package on the target or during image creation when a package is included in an image. To add a post-installation script to a package, add a `pkg_postinst:PACKAGENAME()` function to the recipe file (`.bb`) and replace `PACKAGENAME` with the name of the package you want to attach to the `postinst` script. To apply the post-installation script to the main package for the recipe, which is usually what is required, specify `${PN}` in place of `PACKAGENAME`.

A post-installation function has the following structure:

```
pkg_postinst:PACKAGENAME() {
    # Commands to carry out
}
```

The script defined in the post-installation function is called when the root filesystem is created. If the script succeeds, the package is marked as installed.

### Nota

Any RPM post-installation script that runs on the target should return a 0 exit code. RPM does not allow non-zero exit codes for these scripts, and the RPM package manager will cause the package to fail installation on the target.

Sometimes it is necessary for the execution of a post-installation script to be delayed until the first boot. For example, the script might need to be executed on the device itself. To delay script execution until boot time, you must explicitly mark post installs to defer to the target. You can use `pkg_postinst_ontarget()` or call `postinst_intercept_delay_to_first_boot` from `pkg_postinst()`. Any failure of a `pkg_postinst()` script (including exit 1) triggers an error during the *do\_rootfs* task.

If you have recipes that use `pkg_postinst` function and they require the use of non-standard native tools that have dependencies during root filesystem construction, you need to use the `PACKAGE_WRITE_DEPS` variable in your recipe to list these tools. If you do not use this variable, the tools might be missing and execution of the post-installation script is deferred until first boot. Deferring the script to the first boot is undesirable and impossible for read-only root filesystems.

### Nota

There is equivalent support for pre-install, pre-uninstall, and post-uninstall scripts by way of `pkg_preinst`, `pkg_prerm`, and `pkg_postrm`, respectively. These scripts work in exactly the same way as does `pkg_postinst` with the exception that they run at different times. Also, because of when they run, they are not applicable to being run at image creation time like `pkg_postinst`.

## 8.5.20 Testing

The final step for completing your recipe is to be sure that the software you built runs correctly. To accomplish runtime testing, add the build's output packages to your image and test them on the target.

For information on how to customize your image by adding specific packages, see "*Customizing Images*" section.

## 8.5.21 Esempi

To help summarize how to write a recipe, this section provides some recipe examples given various scenarios:

- *Building a single .c file package*
- *Building a Makefile-based package*
- *Building an Autotooled package*
- *Building a Meson package*
- *Splitting an application into multiple packages*
- *Packaging externally produced binaries*

### Building a Single .c File Package

Building an application from a single file that is stored locally (e.g. under `files`) requires a recipe that has the file listed in the `SRC_URI` variable. Additionally, you need to manually write the `do_compile` and `do_install` tasks. The `S` variable defines the directory containing the source code, which is set to `UNPACKDIR` in this case --- the directory BitBake uses for the build:

```
SUMMARY = "Simple helloworld application"
SECTION = "examples"
LICENSE = "MIT"
LIC_FILES_CHKSUM = "file://${COMMON_LICENSE_DIR}/MIT;
↪md5=0835ade698e0bcf8506ecda2f7b4f302"

SRC_URI = "file://helloworld.c"

S = "${UNPACKDIR}"

do_compile() {
    ${CC} ${LDFLAGS} helloworld.c -o helloworld
}

do_install() {
    install -d ${D}${bindir}
    install -m 0755 helloworld ${D}${bindir}
}
```

By default, the `helloworld`, `helloworld-dbg`, and `helloworld-dev` packages are built. For information on how to customize the packaging process, see the "*Splitting an Application into Multiple Packages*" section.

## Building a Makefile-Based Package

Applications built with GNU `make` require a recipe that has the source archive listed in `SRC_URI`. You do not need to add a `do_compile` step since by default BitBake starts the `make` command to compile the application. If you need additional `make` options, you should store them in the `EXTRA_OEMAKE` or `PACKAGECONFIG_CONFGARGS` variables. BitBake passes these options into the GNU `make` invocation. Note that a `do_install` task is still required. Otherwise, BitBake runs an empty `do_install` task by default.

Some applications might require extra parameters to be passed to the compiler. For example, the application might need an additional header path. You can accomplish this by adding to the `CFLAGS` variable. The following example shows this:

```
CFLAGS:prepend = "-I ${S}/include "
```

In the following example, `lz4` is a makefile-based package:

```
SUMMARY = "Extremely Fast Compression algorithm"
DESCRIPTION = "LZ4 is a very fast lossless compression algorithm, providing
↳compression speed at 400 MB/s per core, scalable with multi-cores CPU. It also
↳features an extremely fast decoder, with speed in multiple GB/s per core,
↳typically reaching RAM speed limits on multi-core systems."
HOMEPAGE = "https://github.com/lz4/lz4"

LICENSE = "BSD-2-Clause | GPL-2.0-only"
LIC_FILES_CHKSUM = "file://lib/LICENSE;md5=ebc2ea4814a64de7708f1571904b32cc \
                    file://programs/COPYING;md5=b234ee4d69f5fce4486a80fdaf4a4263 \
                    file://LICENSE;md5=d57c0d21cb917fb4e0af2454aa48b956 \
                    "

PE = "1"

SRCREV = "d44371841a2f1728a3f36839fd4b7e872d0927d3"

SRC_URI = "git://github.com/lz4/lz4.git;branch=release;protocol=https \
          file://CVE-2021-3520.patch \
          "

UPSTREAM_CHECK_GITTAGREGEX = "v(?P<pver>.*)"

CVE_STATUS[CVE-2014-4715] = "fixed-version: Fixed in r118, which is larger than
↳the current version"

EXTRA_OEMAKE = "PREFIX=${prefix} CC='${CC}' CFLAGS='${CFLAGS}' DESTDIR=${D} LIBDIR=
↳${libdir} INCLUDEDIR=${includedir} BUILD_STATIC=no"

do_install() {
    oe_runmake install
```

(continues on next page)

(continua dalla pagina precedente)

```
}  
  
BBCLASSEXTEND = "native nativesdk"
```

## Building an Autotooled Package

Applications built with the Autotools such as `autoconf` and `automake` require a recipe that has a source archive listed in `SRC_URI` and also inherit the `autotools*` class, which contains the definitions of all the steps needed to build an Autotool-based application. The result of the build is automatically packaged. And, if the application uses NLS for localization, packages with local information are generated (one package per language). Here is one example: (`hello_2.3.bb`):

```
SUMMARY = "GNU Helloworld application"  
SECTION = "examples"  
LICENSE = "GPL-2.0-or-later"  
LIC_FILES_CHKSUM = "file://COPYING;md5=751419260aa954499f7abaabaa882bbe"  
  
SRC_URI = "${GNU_MIRROR}/hello/hello-${PV}.tar.gz"  
  
inherit autotools gettext
```

The variable `LIC_FILES_CHKSUM` is used to track source license changes as described in the "[Tracking License Changes](#)" section in the Yocto Project Overview and Concepts Manual. You can quickly create Autotool-based recipes in a manner similar to the previous example.

## Building a Meson Package

Applications built with the [Meson build system](#) just need a recipe that has sources described in `SRC_URI` and inherits the `meson` class.

The `ipcalc` recipe is a simple example of an application without dependencies:

```
SUMMARY = "Tool to assist in network address calculations for IPv4 and IPv6."  
HOMEPAGE = "https://gitlab.com/ipcalc/ipcalc"  
  
SECTION = "net"  
  
LICENSE = "GPL-2.0-only"  
LIC_FILES_CHKSUM = "file://COPYING;md5=b234ee4d69f5fce4486a80fdaf4a4263"  
  
SRC_URI = "git://gitlab.com/ipcalc/ipcalc.git;protocol=https;branch=master"  
SRCREV = "4c4261a47f355946ee74013d4f5d0494487cc2d6"  
  
inherit meson
```

Applications with dependencies are likely to inherit the *pkgconfig* class, as `pkg-config` is the default method used by Meson to find dependencies and compile applications against them.

## Splitting an Application into Multiple Packages

You can use the variables *PACKAGES* and *FILES* to split an application into multiple packages.

Here is an example that uses the `libxpm` recipe. By default, this recipe generates a single package that contains the library along with a few binaries. You can modify the recipe to split the binaries into separate packages:

```
require xorg-lib-common.inc

SUMMARY = "Xpm: X Pixmap extension library"
LICENSE = "MIT"
LIC_FILES_CHKSUM = "file://COPYING;md5=51f4270b012ecd4ab1a164f5f4ed6cf7"
DEPENDS += "libxext libsm libxt"
PE = "1"

XORG_PN = "libXpm"

PACKAGES += "sxpm cxpm"
FILES:cxpm = "${bindir}/cxpm"
FILES:sxpm = "${bindir}/sxpm"
```

In the previous example, we want to ship the `sxpm` and `cxpm` binaries in separate packages. Since `bindir` would be packaged into the main *PN* package by default, we prepend the *PACKAGES* variable so additional package names are added to the start of list. This results in the extra `FILES:*` variables then containing information that define which files and directories go into which packages. Files included by earlier packages are skipped by latter packages. Thus, the main *PN* package does not include the above listed files.

## Packaging Externally Produced Binaries

Sometimes, you need to add pre-compiled binaries to an image. For example, suppose that there are binaries for proprietary code, created by a particular division of a company. Your part of the company needs to use those binaries as part of an image that you are building using the OpenEmbedded build system. Since you only have the binaries and not the source code, you cannot use a typical recipe that expects to fetch the source specified in *SRC\_URI* and then compile it.

One method is to package the binaries and then install them as part of the image. Generally, it is not a good idea to package binaries since, among other things, it can hinder the ability to reproduce builds and could lead to compatibility problems with ABI in the future. However, sometimes you have no choice.

The easiest solution is to create a recipe that uses the *bin\_package* class and to be sure that you are using default locations for build artifacts. In most cases, the *bin\_package* class handles "skipping" the configure and compile steps as well as sets things up to grab packages from the appropriate area. In particular, this class sets `noexec` on both the *do\_configure* and *do\_compile* tasks, sets `FILES:${PN}` to `"/*"` so that it picks up all files, and sets up a *do\_install* task, which effectively copies all files from `${S}` to `${D}`. The *bin\_package* class works well when the files extracted into

`${S}` are already laid out in the way they should be laid out on the target. For more information on these variables, see the *FILES*, *PN*, *S*, and *D* variables in the Yocto Project Reference Manual's variable glossary.

#### Nota

- Using *DEPENDS* is a good idea even for components distributed in binary form, and is often necessary for shared libraries. For a shared library, listing the library dependencies in *DEPENDS* makes sure that the libraries are available in the staging sysroot when other recipes link against the library, which might be necessary for successful linking.
- Using *DEPENDS* also allows runtime dependencies between packages to be added automatically. See the "*Dipendenze di Runtime Aggiunte Automaticamente*" section in the Yocto Project Overview and Concepts Manual for more information.

If you cannot use the *bin\_package* class, you need to be sure you are doing the following:

- Create a recipe where the *do\_configure* and *do\_compile* tasks do nothing: It is usually sufficient to just not define these tasks in the recipe, because the default implementations do nothing unless a Makefile is found in `${S}`.

If `${S}` might contain a Makefile, or if you inherit some class that replaces *do\_configure* and *do\_compile* with custom versions, then you can use the `[noexec]` flag to turn the tasks into no-ops, as follows:

```
do_configure[noexec] = "1"
do_compile[noexec] = "1"
```

Unlike *Deleting a Task*, using the flag preserves the dependency chain from the *do\_fetch*, *do\_unpack*, and *do\_patch* tasks to the *do\_install* task.

- Make sure your *do\_install* task installs the binaries appropriately.
- Ensure that you set up *FILES* (usually `FILES:${PN}`) to point to the files you have installed, which of course depends on where you have installed them and whether those files are in different locations than the defaults.

As a basic example of a *bin\_package*-style recipe, consider this snippet from the *wireless-regdb* recipe file, which fetches a single tarball of binary content and manually installs with no need for any configuration or compilation:

```
SRC_URI = "https://www.kernel.org/pub/software/network/${BPN}/${BP}.tar.xz"
SRC_URI[sha256sum] =
→ "57f8e7721cf5a880c13ae0c202eddb21092a060d45f9e9c59bcd2a8272bfa456"

inherit bin_package allarch

do_install() {
    install -d -m0755 ${D}${nonarch_libdir}/crda
    install -d -m0755 ${D}${sysconfdir}/wireless-regdb/pubkeys
    install -m 0644 regulatory.bin ${D}${nonarch_libdir}/crda/regulatory.bin
    install -m 0644 wens.key.pub.pem ${D}${sysconfdir}/wireless-regdb/pubkeys/wens.
```

(continues on next page)



(continua dalla pagina precedente)

```

↪key.pub.pem
    install -m 0644 -D regulatory.db ${D}${nonarch_base_libdir}/firmware/
↪regulatory.db
    install -m 0644 regulatory.db.p7s ${D}${nonarch_base_libdir}/firmware/
↪regulatory.db.p7s
}

```

## 8.5.22 Following Recipe Style Guidelines

When writing recipes, it is good to conform to existing style guidelines. See the "*Guida di Stile per le Ricette*" in the Yocto Project and OpenEmbedded Contributor Guide for reference.

It is common for existing recipes to deviate a bit from this style. However, aiming for at least a consistent style is a good idea. Some practices, such as omitting spaces around = operators in assignments or ordering recipe components in an erratic way, are widely seen as poor style.

## 8.5.23 Recipe Syntax

Understanding recipe file syntax is important for writing recipes. The following list overviews the basic items that make up a BitBake recipe file. For more complete BitBake syntax descriptions, see the "[Syntax and Operators](#)" chapter of the BitBake User Manual.

- *Variable Assignments and Manipulations:* Variable assignments allow a value to be assigned to a variable. The assignment can be static text or might include the contents of other variables. In addition to the assignment, appending and prepending operations are also supported.

The following example shows some of the ways you can use variables in recipes:

```

S = "${UNPACKDIR}/postfix-${PV}"
CFLAGS += "-DNO_ASM"
CFLAGS:append = " --enable-important-feature"

```

- *Functions:* Functions provide a series of actions to be performed. You usually use functions to override the default implementation of a task function or to complement a default function (i.e. append or prepend to an existing function). Standard functions use `sh` shell syntax, although access to OpenEmbedded variables and internal methods are also available.

Here is an example function from the `sed` recipe:

```

do_install () {
    autotools_do_install
    install -d ${D}${base_bindir}
    if [ ! ${D}${bindir} -ef ${D}${base_bindir} ]; then
        mv ${D}${bindir}/sed ${D}${base_bindir}/sed
        rmdir ${D}${bindir}/
    fi
}

```

It is also possible to implement new functions that are called between existing tasks as long as the new functions are not replacing or complementing the default functions. You can implement functions in Python instead of shell. Both of these options are not seen in the majority of recipes.

- **Keywords:** BitBake recipes use only a few keywords. You use keywords to include common functions (`inherit`), load parts of a recipe from other files (`include` and `require`) and export variables to the environment (`export`).

The following example shows the use of some of these keywords:

```
export POSTCONF = "${STAGING_BINDIR}/postconf"
inherit autoconf
require otherfile.inc
```

- **Comments (#):** Any lines that begin with the hash character (#) are treated as comment lines and are ignored:

```
# This is a comment
```

This next list summarizes the most important and most commonly used parts of the recipe syntax. For more information on these parts of the syntax, you can reference the "[Syntax and Operators](#)" chapter in the BitBake User Manual.

- **Line Continuation (\):** Use the backward slash (\) character to split a statement over multiple lines. Place the slash character at the end of the line that is to be continued on the next line:

```
VAR = "A really long \
line"
```

#### Nota

You cannot have any characters including spaces or tabs after the slash character.

- **Using Variables (\${VARNAME}):** Use the \${VARNAME} syntax to access the contents of a variable:

```
SRC_URI = "${SOURCEFORGE_MIRROR}/libpng/zlib-${PV}.tar.gz"
```

#### Nota

It is important to understand that the value of a variable expressed in this form does not get substituted automatically. The expansion of these expressions happens on-demand later (e.g. usually when a function that makes reference to the variable executes). This behavior ensures that the values are most appropriate for the context in which they are finally used. On the rare occasion that you do need the variable expression to be expanded immediately, you can use the `:=` operator instead of `=` when you make the assignment, but this is not generally needed.

- **Quote All Assignments ("value"):** Use double quotes around values in all variable assignments (e.g. "value"). Here is an example:

```
VAR1 = "${OTHERVAR}"
VAR2 = "The version is ${PV}"
```

- *Conditional Assignment (?=)*: Conditional assignment is used to assign a value to a variable, but only when the variable is currently unset. Use the question mark followed by the equal sign (|=) to make a "soft" assignment used for conditional assignment. Typically, "soft" assignments are used in *configuration files* for variables that are allowed to come through from the external environment.

Here is an example where VAR1 is set to "New value" if it is currently empty. However, if VAR1 has already been set, it remains unchanged:

```
VAR1 |= "New value"
```

In this next example, VAR1 is left with the value "Original value":

```
VAR1 = "Original value"
VAR1 |= "New value"
```

- *Appending (+=)*: Use the plus character followed by the equals sign (+=) to append values to existing variables.

#### Nota

This operator adds a space between the existing content of the variable and the new content.

Here is an example:

```
SRC_URI += "file://fix-makefile.patch"
```

- *Prepending (+=)*: Use the equals sign followed by the plus character (+=) to prepend values to existing variables.

#### Nota

This operator adds a space between the new content and the existing content of the variable.

Here is an example:

```
VAR += "Starts"
```

- *Appending (:append)*: Use the :append operator to append values to existing variables. This operator does not add any additional space. Also, the operator is applied after all the +=, and += operators have been applied and after all = assignments have occurred. This means that if :append is used in a recipe, it can only be overridden by another layer using the special :remove operator, which in turn will prevent further layers from adding it back.

The following example shows the space being explicitly added to the start to ensure the appended value is not merged with the existing value:

```
CFLAGS:append = " --enable-important-feature"
```

You can also use the `:append` operator with overrides, which results in the actions only being performed for the specified target or machine:

```
CFLAGS:append:sh4 = " --enable-important-sh4-specific-feature"
```

- *Prepending (:prepend):* Use the `:prepend` operator to prepend values to existing variables. This operator does not add any additional space. Also, the operator is applied after all the `+=`, and `=+` operators have been applied and after all `=` assignments have occurred.

The following example shows the space being explicitly added to the end to ensure the prepended value is not merged with the existing value:

```
CFLAGS:prepend = "-I${S}/myincludes "
```

You can also use the `:prepend` operator with overrides, which results in the actions only being performed for the specified target or machine:

```
CFLAGS:prepend:sh4 = "-I${S}/myincludes "
```

- *Overrides:* You can use overrides to set a value conditionally, typically based on how the recipe is being built. For example, to set the `KBRANCH` variable's value to "standard/base" for any target `MACHINE`, except for `qemuarm` where it should be set to "standard/arm-versatile-926ejs", you would do the following:

```
KBRANCH = "standard/base"
KBRANCH:qemuarm = "standard/arm-versatile-926ejs"
```

Overrides are also used to separate alternate values of a variable in other situations. For example, when setting variables such as `FILES` and `RDEPENDS` that are specific to individual packages produced by a recipe, you should always use an override that specifies the name of the package.

- *Indentation:* Use spaces for indentation rather than tabs. For shell functions, both currently work. However, it is a policy decision of the Yocto Project to use tabs in shell functions. Realize that some layers have a policy to use spaces for all indentation.
- *Using Python for Complex Operations:* For more advanced processing, it is possible to use Python code during variable assignments (e.g. search and replacement on a variable).

You indicate Python code using the `${@python_code}` syntax for the variable assignment:

```
SRC_URI = "ftp://ftp.info-zip.org/pub/infozip/src/zip${@d.getVar('PV',1)}.
↪replace('.', ' ').tgz"
```

- *Shell Function Syntax:* Write shell functions as if you were writing a shell script when you describe a list of actions to take. You should ensure that your script works with a generic `sh` and that it does not require any `bash` or other shell-specific functionality. The same considerations apply to various system utilities (e.g. `sed`, `grep`, `awk`, and so forth) that you might wish to use. If in doubt, you should check with multiple implementations --- including those from BusyBox.

## 8.6 Adding a New Machine

Adding a new machine to the Yocto Project is a straightforward process. This section describes how to add machines that are similar to those that the Yocto Project already supports.

### Nota

Although well within the capabilities of the Yocto Project, adding a totally new architecture might require changes to `gcc/glibc` and to the site information, which is beyond the scope of this manual.

For a complete example that shows how to add a new machine, see the "*Creazione di un Nuovo Layer BSP Tramite lo Script bitbake-layers*" section in the Yocto Project Board Support Package (BSP) Developer's Guide.

### 8.6.1 Adding the Machine Configuration File

To add a new machine, you need to add a new machine configuration file to the layer's `conf/machine` directory. This configuration file provides details about the device you are adding.

The OpenEmbedded build system uses the root name of the machine configuration file to reference the new machine. For example, given a machine configuration file named `crownbay.conf`, the build system recognizes the machine as "crownbay".

The most important variables you must set in your machine configuration file or include from a lower-level configuration file are as follows:

- `TARGET_ARCH` (e.g. "arm")
- `PREFERRED_PROVIDER_virtual/kernel`
- `MACHINE_FEATURES` (e.g. "screen wifi")

You might also need these variables:

- `SERIAL_CONSOLES` (e.g. "115200;ttyS0 115200;ttyS1")
- `KERNEL_IMAGETYPE` (e.g. "zImage")
- `IMAGE_FSTYPES` (e.g. "tar.gz jffs2")

You can find full details on these variables in the reference section. You can leverage existing machine `.conf` files from `meta-yocto-bsp/conf/machine/`.

### 8.6.2 Adding a Kernel for the Machine

The OpenEmbedded build system needs to be able to build a kernel for the machine. You need to either create a new kernel recipe for this machine, or extend an existing kernel recipe. You can find several kernel recipe examples in the Source Directory at `meta/recipes-kernel/linux` that you can use as references.

If you are creating a new kernel recipe, normal recipe-writing rules apply for setting up a `SRC_URI`. Thus, you need to specify any necessary patches and set `S` to point at the source code. You need to create a `do_configure` task that configures the unpacked kernel with a `defconfig` file. You can do this by using a `make defconfig` command or, more commonly, by copying in a suitable `defconfig` file and then running `make oldconfig`. By making use of

inherit kernel and potentially some of the `linux-*.inc` files, most other functionality is centralized and the defaults of the class normally work well.

If you are extending an existing kernel recipe, it is usually a matter of adding a suitable `defconfig` file. The file needs to be added into a location similar to `defconfig` files used for other machines in a given kernel recipe. A possible way to do this is by listing the file in the `SRC_URI` and adding the machine to the expression in `COMPATIBLE_MACHINE`:

```
COMPATIBLE_MACHINE = '(qemux86|qemumips)'
```

For more information on `defconfig` files, see the "[Changing the Configuration](#)" section in the Yocto Project Linux Kernel Development Manual.

### 8.6.3 Adding a Formfactor Configuration File

A formfactor configuration file provides information about the target hardware for which the image is being built and information that the build system cannot obtain from other sources such as the kernel. Some examples of information contained in a formfactor configuration file include framebuffer orientation, whether or not the system has a keyboard, the positioning of the keyboard in relation to the screen, and the screen resolution.

The build system uses reasonable defaults in most cases. However, if customization is necessary, you need to create a `machconfig` file in the `meta/recipes-bsp/formfactor/files` directory. This directory contains directories for specific machines such as `qemuarm` and `qemux86`. For information about the settings available and the defaults, see the `meta/recipes-bsp/formfactor/files/config` file found in the same area.

Here is an example for "qemuarm" machine:

```
HAVE_TOUCHSCREEN=1
HAVE_KEYBOARD=1
DISPLAY_CAN_ROTATE=0
DISPLAY_ORIENTATION=0
#DISPLAY_WIDTH_PIXELS=640
#DISPLAY_HEIGHT_PIXELS=480
#DISPLAY_BPP=16
DISPLAY_DPI=150
DISPLAY_SUBPIXEL_ORDER=vrgb
```

## 8.7 Upgrading Recipes

Over time, upstream developers publish new versions for software built by layer recipes. It is recommended to keep recipes up-to-date with upstream version releases.

While there are several methods to upgrade a recipe, you might consider checking on the upgrade status of a recipe first. You can do so using the `devtool check-upgrade-status` command. See the "[Checking on the Upgrade Status of a Recipe](#)" section in the Yocto Project Reference Manual for more information.

The remainder of this section describes three ways you can upgrade a recipe. You can use the Automated Upgrade Helper (AUH) to set up automatic version upgrades. Alternatively, you can use `devtool upgrade` to set up semi-automatic version upgrades. Finally, you can manually upgrade a recipe by editing the recipe itself.

### 8.7.1 Using the Auto Upgrade Helper (AUH)

The AUH utility works in conjunction with the OpenEmbedded build system in order to automatically generate upgrades for recipes based on new versions being published upstream. Use AUH when you want to create a service that performs the upgrades automatically and optionally sends you an email with the results.

AUH allows you to update several recipes with a single use. You can also optionally perform build and integration tests using images with the results saved to your hard drive and emails of results optionally sent to recipe maintainers. Finally, AUH creates Git commits with appropriate commit messages in the layer's tree for the changes made to recipes.

#### Nota

In some conditions, you should not use AUH to upgrade recipes and should instead use either `devtool upgrade` or upgrade your recipes manually:

- When AUH cannot complete the upgrade sequence. This situation usually results because custom patches carried by the recipe cannot be automatically rebased to the new version. In this case, `devtool upgrade` allows you to manually resolve conflicts.
- When for any reason you want fuller control over the upgrade process. For example, when you want special arrangements for testing.

The following steps describe how to set up the AUH utility:

1. *Be Sure the Development Host is Set Up:* You need to be sure that your development host is set up to use the Yocto Project. For information on how to set up your host, see the "[Preparing the Build Host](#)" section.
2. *Make Sure Git is Configured:* The AUH utility requires Git to be configured because AUH uses Git to save upgrades. Thus, you must have Git user and email configured. The following command shows your configurations:

```
$ git config --list
```

If you do not have the user and email configured, you can use the following commands to do so:

```
$ git config --global user.name some_name
$ git config --global user.email username@domain.com
```

3. *Clone the AUH Repository:* To use AUH, you must clone the repository onto your development host. The following command uses Git to create a local copy of the repository on your system:

```
$ git clone https://git.yoctoproject.org/auto-upgrade-helper
Cloning into 'auto-upgrade-helper'... remote: Counting objects: 768, done.
remote: Compressing objects: 100% (300/300), done.
remote: Total 768 (delta 499), reused 703 (delta 434)
Receiving objects: 100% (768/768), 191.47 KiB | 98.00 KiB/s, done.
Resolving deltas: 100% (499/499), done.
Checking connectivity... done.
```

AUH is not part of the *OpenEmbedded-Core (OE-Core)* or *Poky* repositories.

4. *Create a Dedicated Build Directory:* Create a new *Setup* with `bitbake-setup` or manually run the `oe-init-build-env` script to create a fresh *Build Directory* that you use exclusively for running the AUH utility:

```
$ source layers/openembedded-core/oe-init-build-env your_AUH_build_directory
```

Re-using an existing *Build Directory* and its configurations is not recommended as existing settings could cause AUH to fail or behave undesirably.

5. *Make Configurations in Your Local Configuration File:* Several settings are needed in the `build/conf/local.conf` file in the build directory you just created for AUH. Make these following configurations:

- If you want to enable *Build History*, which is optional, you need the following lines in the `build/conf/local.conf` file:

```
INHERIT += "buildhistory"
BUILDHISTORY_COMMIT = "1"
```

With this configuration and a successful upgrade, a build history "diff" file appears in the `upgrade-helper/work/recipe/buildhistory-diff.txt` file found in your *Build Directory*.

- If you want to enable testing through the *testimage* class, which is optional, you need to have the following set in your `build/conf/local.conf` file:

```
IMAGE_CLASSES += "testimage"
```

#### Nota

If your distro does not enable by default `ptest`, which *Poky* does, you need the following in your `build/conf/local.conf` file:

```
DISTRO_FEATURES:append = " ptest"
```

6. *Optionally Start a vncserver:* If you are running in a server without an X11 session, you need to start a vncserver:

```
$ vncserver :1
$ export DISPLAY=:1
```

7. *Create and Edit an AUH Configuration File:* You need to have the `upgrade-helper/upgrade-helper.conf` configuration file in your *Build Directory*. You can find a sample configuration file in the [AUH source repository](#).

Read through the sample file and make configurations as needed. For example, if you enabled build history in your `build/conf/local.conf` as described earlier, you must enable it in `upgrade-helper.conf`.

Also, if you are using the default `maintainers.inc` file supplied in *OpenEmbedded-Core (OE-Core)* and you do not set a `"maintainers_whitelist"` or `"global_maintainer_override"` in the `upgrade-helper.conf` configuration, and you specify `"-e all"` on the AUH command-line, the utility automatically sends out emails to all the default maintainers. Please avoid this.



This next set of examples describes how to use the AUH:

- *Upgrading a Specific Recipe:* To upgrade a specific recipe, use the following form:

```
$ upgrade-helper.py recipe_name
```

For example, this command upgrades the `xmodmap` recipe:

```
$ upgrade-helper.py xmodmap
```

- *Upgrading a Specific Recipe to a Particular Version:* To upgrade a specific recipe to a particular version, use the following form:

```
$ upgrade-helper.py recipe_name -t version
```

For example, this command upgrades the `xmodmap` recipe to version 1.2.3:

```
$ upgrade-helper.py xmodmap -t 1.2.3
```

- *Upgrading all Recipes to the Latest Versions and Suppressing Email Notifications:* To upgrade all recipes to their most recent versions and suppress the email notifications, use the following command:

```
$ upgrade-helper.py all
```

- *Upgrading all Recipes to the Latest Versions and Send Email Notifications:* To upgrade all recipes to their most recent versions and send email messages to maintainers for each attempted recipe as well as a status email, use the following command:

```
$ upgrade-helper.py -e all
```

Once you have run the AUH utility, you can find the results in the AUH *Build Directory*:

```
${BUILDDIR}/upgrade-helper/timestamp
```

The AUH utility also creates recipe update commits from successful upgrade attempts in the layer tree.

You can easily set up to run the AUH utility on a regular basis by using a cron job. See the `weeklyjob.sh` file distributed with the utility for an example.

## 8.7.2 Using `devtool upgrade`

As mentioned earlier, an alternative method for upgrading recipes to newer versions is to use *devtool upgrade*. You can read about `devtool upgrade` in general in the "*Use devtool upgrade to Create a Version of the Recipe that Supports a Newer Version of the Software*" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) Manual.

To see all the command-line options available with `devtool upgrade`, use the following help command:

```
$ devtool upgrade -h
```

If you want to find out what version a recipe is currently at upstream without any attempt to upgrade your local version of the recipe, you can use the following command:

```
$ devtool latest-version recipe_name
```

As mentioned in the previous section describing AUH, `devtool upgrade` works in a less-automated manner than AUH. Specifically, `devtool upgrade` only works on a single recipe that you name on the command line, cannot perform build and integration testing using images, and does not automatically generate commits for changes in the source tree. Despite all these "limitations", `devtool upgrade` updates the recipe file to the new upstream version and attempts to rebase custom patches contained by the recipe as needed.

#### Nota

AUH uses much of `devtool upgrade` behind the scenes making AUH somewhat of a "wrapper" application for `devtool upgrade`.

A typical scenario involves having used Git to clone an upstream repository that you use during build operations. Because you have built the recipe in the past, the layer is likely added to your configuration already. If for some reason, the layer is not added, you could add it easily using the "*bitbake-layers*" script. For example, suppose you use the `nano.bb` recipe from the `meta-oe` layer in the `meta-openembedded` repository. For this example, assume that the layer has been cloned into following area:

```
/home/scottrif/bitbake-builds/layers/meta-openembedded
```

The following command from your *Build Directory* adds the layer to your build configuration (i.e. `${BUILDDIR}/conf/bblayers.conf`):

```
$ bitbake-layers add-layer /home/scottrif/bitbake-builds/layers/meta-openembedded/
↪meta-oe
NOTE: Starting bitbake server...
Parsing recipes: 100% |#####| Time: 0:00:55
Parsing of 1431 .bb files complete (0 cached, 1431 parsed). 2040 targets, 56↪
↪skipped, 0 masked, 0 errors.
Removing 12 recipes from the x86_64 sysroot: 100% |#####| Time: 0:00:00
Removing 1 recipes from the x86_64_i586 sysroot: 100% |#####| Time: 0:00:00
Removing 5 recipes from the i586 sysroot: 100% |#####| Time: 0:00:00
Removing 5 recipes from the qemu86 sysroot: 100% |#####| Time: 0:00:00
```

For this example, assume that the `nano.bb` recipe that is upstream has a 2.9.3 version number. However, the version in the local repository is 2.7.4. The following command from your build directory automatically upgrades the recipe for you:

```
$ devtool upgrade nano -V 2.9.3
NOTE: Starting bitbake server...
NOTE: Creating workspace layer in /home/scottrif/bitbake-builds/build/workspace
Parsing recipes: 100% |#####| Time: 0:00:46
```

(continues on next page)

(continua dalla pagina precedente)

```

Parsing of 1431 .bb files complete (0 cached, 1431 parsed). 2040 targets, 56
↳skipped, 0 masked, 0 errors.
NOTE: Extracting current version source...
NOTE: Resolving any missing task queue dependencies
    .
    .
    .
NOTE: Executing SetScene Tasks
NOTE: Executing RunQueue Tasks
NOTE: Tasks Summary: Attempted 74 tasks of which 72 didn't need to be rerun and
↳all succeeded.
Adding changed files: 100% |#####| Time: 0:00:00
NOTE: Upgraded source extracted to /home/scottrif/bitbake-builds/build/workspace/
↳sources/nano
NOTE: New recipe is /home/scottrif/bitbake-builds/build/workspace/recipes/nano/
↳nano_2.9.3.bb

```

**i Nota**

Using the `-v` option is not necessary. Omitting the version number causes `devtool upgrade` to upgrade the recipe to the most recent version.

Continuing with this example, you can use `devtool build` to build the newly upgraded recipe:

```

$ devtool build nano
NOTE: Starting bitbake server...
Loading cache: 100% |#####| Time: 0:00:01
↳#####
Loaded 2040 entries from dependency cache.
Parsing recipes: 100% |#####| Time: 0:00:00
↳#####
Parsing of 1432 .bb files complete (1431 cached, 1 parsed). 2041 targets, 56
↳skipped, 0 masked, 0 errors.
NOTE: Resolving any missing task queue dependencies
    .
    .
    .
NOTE: Executing SetScene Tasks
NOTE: Executing RunQueue Tasks
NOTE: nano: compiling from external source tree /home/scottrif/bitbake-builds/
↳build/workspace/sources/nano
NOTE: Tasks Summary: Attempted 520 tasks of which 304 didn't need to be rerun and
↳all succeeded.

```

Within the `devtool upgrade` workflow, you can deploy and test your rebuilt software. For this example, however, running `devtool finish` cleans up the workspace once the source in your workspace is clean. This usually means using Git to stage and submit commits for the changes generated by the upgrade process.

Once the tree is clean, you can clean things up in this example with the following command from the `${BUILDDIR}/workspace/sources/nano` directory:

```
$ devtool finish nano meta-oe
NOTE: Starting bitbake server...
Loading cache: 100% |#####|
↳#####| Time: 0:00:00
Loaded 2040 entries from dependency cache.
Parsing recipes: 100% |#####|
↳#####| Time: 0:00:01
Parsing of 1432 .bb files complete (1431 cached, 1 parsed). 2041 targets, 56_
↳skipped, 0 masked, 0 errors.
NOTE: Adding new patch 0001-nano.bb-Stuff-I-changed-when-upgrading-nano.bb.patch
NOTE: Updating recipe nano_2.9.3.bb
NOTE: Removing file /home/scottrif/bitbake-builds/layers/meta-openembedded/meta-oe/
↳recipes-support/nano/nano_2.7.4.bb
NOTE: Moving recipe file to /home/scottrif/bitbake-builds/layers/meta-openembedded/
↳meta-oe/recipes-support/nano
NOTE: Leaving source tree /home/scottrif/bitbake-builds/build/workspace/sources/
↳nano as-is; if you no longer need it then please delete it manually
```

Using the `devtool finish` command cleans up the workspace and creates a patch file based on your commits. The tool puts all patch files back into the source directory in a sub-directory named `nano` in this case.

### 8.7.3 Manually Upgrading a Recipe

If for some reason you choose not to upgrade recipes using *Using the Auto Upgrade Helper (AUH)* or by *Using devtool upgrade*, you can manually edit the recipe files to upgrade the versions.

#### Nota

Manually updating multiple recipes scales poorly and involves many steps. The recommendation to upgrade recipe versions is through AUH or `devtool upgrade`, both of which automate some steps and provide guidance for others needed for the manual process.

To manually upgrade recipe versions, follow these general steps:

1. *Change the Version:* Rename the recipe such that the version (i.e. the *PV* part of the recipe name) changes appropriately. If the version is not part of the recipe name, change the value as it is set for *PV* within the recipe itself.
2. *Update SRCREV if Needed:* If the source code your recipe builds is fetched from Git or some other version control system, update *SRCREV* to point to the commit hash that matches the new version.

3. *Build the Software:* Try to build the recipe using BitBake. Typical build failures include the following:

- License statements were updated for the new version. For this case, you need to review any changes to the license and update the values of `LICENSE` and `LIC_FILES_CHKSUM` as needed.

**Nota**

License changes are often inconsequential. For example, the license text's copyright year might have changed.

- Custom patches carried by the older version of the recipe might fail to apply to the new version. For these cases, you need to review the failures. Patches might not be necessary for the new version of the software if the upgraded version has fixed those issues. If a patch is necessary and failing, you need to rebase it into the new version.
4. *Optionally Attempt to Build for Several Architectures:* Once you successfully build the new software for a given architecture, you could test the build for other architectures by changing the `MACHINE` variable and rebuilding the software. This optional step is especially important if the recipe is to be released publicly.
5. *Check the Upstream Change Log or Release Notes:* Checking both these reveals if there are new features that could break backwards-compatibility. If so, you need to take steps to mitigate or eliminate that situation.
6. *Optionally Create a Bootable Image and Test:* If you want, you can test the new software by booting it onto actual hardware.
7. *Create a Commit with the Change in the Layer Repository:* After all builds work and any testing is successful, you can create commits for any changes in the layer holding your upgraded recipe.

## 8.8 Finding Temporary Source Code

You might find it helpful during development to modify the temporary source code used by recipes to build packages. For example, suppose you are developing a patch and you need to experiment a bit to figure out your solution. After you have initially built the package, you can iteratively tweak the source code, which is located in the *Build Directory*, and then you can force a re-compile and quickly test your altered code. Once you settle on a solution, you can then preserve your changes in the form of patches.

During a build, the unpacked temporary source code used by recipes to build packages is available in the *Build Directory* as defined by the `S` variable. Below is the default value for the `S` variable as defined in the `meta/conf/bitbake.conf` configuration file in *OpenEmbedded-Core (OE-Core)*:

```
S = "${UNPACKDIR}/${BP}"
```

You should be aware that many recipes override the `S` variable when the default isn't accurate.

**Nota**

The `BP` represents the base recipe name, which consists of the name and version:

```
BP = "${BPN}-${PV}"
```

This matches the location that the git fetcher unpacks to, and usually matches unpacked content of release tarballs (e.g. they contain a single directory which matches value of `BP` exactly).

The path to the unpack directory for the recipe (*UNPACKDIR*) is defined as follows:

```
${WORKDIR}/sources
```

In turn, the path to the work directory for the recipe (*WORKDIR*) is defined as follows:

```
${BASE_WORKDIR}/${MULTIMACH_TARGET_SYS}/${PN}/${PV}
```

The actual directory depends on several things:

- *BASE\_WORKDIR*: The top-level build output directory.
- *MULTIMACH\_TARGET\_SYS*: The target system identifier.
- *PN*: The recipe name.
- *PV*: The recipe version.

As an example, assume a Source Directory top-level folder named `project`, a default *Build Directory* at `project/build`, and a `qemux86-poky-linux` machine target system. Furthermore, suppose your recipe is named `foo_1.3.0.bb`. In this case, the work directory the build system uses to build the package would be as follows:

```
project/build/tmp/work/qemux86-poky-linux/foo/1.3.0
```

#### **i** Nota

If you want to iterate over testing your local changes, the proper way is to use the `devtool` utility.

To learn how to use `devtool` to add, modify, upgrade recipes and more, see the *Using the devtool command-line tool* section of this Development Tasks Manual.

## 8.9 Creating New Configuration Fragments In Your Build

*Configuration Fragments* define top level build configuration features that can be independently enabled and disabled using standard tooling. Such features are made of one or several build configuration statements that are either contained in a fragment file, or are set indirectly using the *Built-in Fragment* mechanism.

This section will describe how to create new fragments for your builds.

There are two kinds of configuration fragments:

- Standard *Configuration Fragments* which are stored in a file. These fragments include a summary and a description, followed by configuration statements.
- *Built-in Fragments* which can be used to assign a value to a single variable and do not require a separate definition file. They are especially useful when a list of possible values is very long (or infinite).

### 8.9.1 Creating A Standard Configuration Fragment

By default, all configuration fragments are located within the `conf/fragments` directory of a *layer*. This location is defined by the `OE_FRAGMENTS_PREFIX` variable which, in turn, is used as a parameter in an `addfragments` directive in `bitbake.conf`.

You can create one or more *configuration fragment* files in your *layer* in this directory. Let's take the following example, where `custom-fragment.conf` is our custom fragment file:

```
meta-custom
├── conf
│   ├── fragments
│   │   └── custom-fragment.conf
│   └── layer.conf
...
```

For our `custom-fragment.conf` file, the following variables **must** be set for our fragment to be considered a valid fragment by the *OpenEmbedded Build System*:

- `BB_CONF_FRAGMENT_SUMMARY`: a one-line summary of this fragment.
- `BB_CONF_FRAGMENT_DESCRIPTION`: a description of this fragment.

#### Nota

The `BB_CONF_FRAGMENT_SUMMARY` and `BB_CONF_FRAGMENT_DESCRIPTION` variables are also passed as parameters in an `addfragments` directive in `bitbake.conf`.

After creating these variables, our custom fragment should look like the following:

Listato 1: custom-fragment.conf

```
BB_CONF_FRAGMENT_SUMMARY = "This fragment sets a limit of 4 bitbake threads and 4_
↪parsing threads"
BB_CONF_FRAGMENT_DESCRIPTION = "This fragment is useful to constrain resource_
↪consumption when the Yocto default \
is causing an overload of host machine's memory and CPU resources."
```

For now, our fragment does not have any additional configuration statement. Let's add the following assignments to our fragment:

Listato 2: custom-fragment.conf (continued)

```
BB_NUMBER_THREADS = "4"
BB_NUMBER_PARSE_THREADS = "4"
```

This means that our fragment can be enabled to set a limit on the number of threads *BitBake* will use with the `BB_NUMBER_THREADS` and `BB_NUMBER_PARSE_THREADS` variables.

For now, our fragment exists and is listed by the *bitbake-config-build list-fragments* command, but is not enabled. To enable this fragment, use the *bitbake-config-build enable-fragment* command:

```
bitbake-config-build enable-fragment meta-custom/custom-fragment
```

### Nota

The `meta-custom` prefix in the above command depends on the name of your layer. This name is defined by the `BBFILE_COLLECTIONS` variable in the `conf/layer.conf` file of your layer.

Standard Configuration fragments can be organized in a more complex way. For example, it's possible to create sub-directories to organize your fragments:

```
meta-custom
├── conf
│   ├── fragments
│   │   ├── networking
│   │   │   └── mirrors.conf
│   │   └── resources
│   │       └── numberthreads.conf
│   └── layer.conf
...

```

In the above example, the `meta-custom/networking/mirrors` and `meta-custom/resources/numberthreads` fragments will be available in your build.

## 8.9.2 Creating A Built-in Fragment

Within the *OpenEmbedded Build System*, Built-in Fragments are defined with the `OE_FRAGMENTS_BUILTIN` variable, which is passed as a parameter in an `addfragments` directive in `bitbake.conf`.

Adding new *Built-in Fragments* can be done by appending the `OE_FRAGMENTS_BUILTIN` variable from your *layer* configuration file:

Listato 3: layer.conf

```
OE_FRAGMENTS_BUILTIN:append = " custom-builtin-fragment:CUSTOM_VARIABLE"
```

### Avvertimento

Make sure to use the `:append` override in the above assignment, as using `+=` can lead to unexpected behavior.



**⚠ Avvertimento**

Due to the way *BitBake* parses files, it is not possible to modify *OE\_FRAGMENTS\_BUILTIN* from any kind of *configuration file*. Setting it from the *layer* configuration file (`conf/layer.conf`) is the retained solution to create new built-in fragments.

You can then use the *bitbake-config-build enable-fragment* command to set a value to the `CUSTOM_VARIABLE` variable:

```
bitbake-config-build enable-fragment custom-builtin-fragment/somevalue
```

## 8.10 Setting Up the Poky Reference Distro Manually

While the default way to set up the *Poky* reference distro is to use *bitbake-setup*, it is also possible to manually set up the environment. This document guides through this setup step-by-step.

**i Nota**

This document will produce a setup similar to what is described in *Build Rapida di un'Immagine con lo Yocto Project*, which shows how to set up *Poky* with *bitbake-setup*.

### 8.10.1 Obtaining The Source Repositories

You can obtain the source repositories required to build the Poky reference distro in two ways described below: *cloning the repositories with Git*, or *downloading the released archives*.

#### Use Git to Clone The Layers

Go to the [Releases](#) page, and choose a release (such as `yocto-6.1_M3`), corresponding to either the latest stable release or a Long Term Support release.

Once you complete the setup instructions for your machine (see the *Requisiti di Sistema* section of the Yocto Project Reference Manual), create a *Source Directory*: the base directory for your project. Throughout the documentation, we will use `bitbake-builds` as the name of the *Source Directory*. Here's how to create it:

```
$ mkdir bitbake-builds
$ cd bitbake-builds
```

You need to get a copy of the different *layers* needed to set up the *Poky* reference distribution on your build host. Use the following commands:

```
$ mkdir layers/
$ git clone -b yocto-6.1_M3 https://git.openembedded.org/bitbake ./layers/bitbake
$ git clone -b yocto-6.1_M3 https://git.openembedded.org/openembedded-core ./
↳ layers/openembedded-core
```

(continues on next page)

(continua dalla pagina precedente)

```
$ git clone -b yocto-6.1_M3 https://git.yoctoproject.org/meta-yocto ./layers/meta-  
→yocto
```

## Using the Source Archives

The Yocto Project also provides source archives of its releases, which are available at <https://downloads.yoctoproject.org/releases/yocto/>. Then, choose the subdirectory containing the release you wish to use, for example `yocto-6.1_M3`.

You will find there source archives of *OpenEmbedded-Core (OE-Core)*, *BitBake*, and *meta-yocto*.

### Nota

The recommended method for accessing Yocto Project components is to *use Git to clone the upstream repository* and work from within the locally cloned repositories.

## 8.10.2 Building dell'Immagine

Seguire i passaggi seguenti per compilare l'immagine. Il processo di compilazione (build) crea un'intera distribuzione Linux, inclusa la toolchain, a partire dai sorgenti.

### Nota

- Se si lavora dietro un firewall e l'host di build non è configurato per i proxy, si potrebbero riscontrare problemi con il processo di build durante il recupero del codice sorgente (ad esempio, errori di fetcher o errori di Git).
- Se non si conoscono le impostazioni del proxy, consulta le risorse della propria infrastruttura di rete locale per ottenere queste informazioni. Un buon punto di partenza potrebbe essere anche controllare le impostazioni del browser web. Infine, si possono trovare maggiori informazioni nella pagina "[Working Behind a Network Proxy](#)" nello Yocto Project Wiki.

1. **Initialize the Build Environment:** From your current working directory, set up a build environment with the following command:

```
$ source ./layers/openembedded-core/oe-init-build-env
```

Among other things, the script creates the *Build Directory*, which is `build` in this case and is located in the *Source Directory*. After the script runs, your current working directory is set to the *Build Directory*. Later, when the build completes, the *Build Directory* contains all the files created during the build.

2. **Examine Your Local Configuration File:** When you set up the build environment, a local configuration file named `build/conf/local.conf` becomes available in a `conf` sub-directory of the *Build Directory*. For this example, the defaults are set to build for a `qemux86-64` target, which is suitable for emulation. The package manager used is set to the RPM package manager.

 **Suggerimento**

È possibile velocizzare significativamente la compilazione e proteggersi dagli errori del fetcher utilizzando i mirror *Cache di Shared State* e abilitando *Equivalenza degli Hash*. Ciò è rilevante solo se la rete e il server utilizzati possono scaricare questi artefatti più velocemente di quanto sarebbe possibile crearli.

To use such mirrors, run the following command:

```
$ bitbake-config-build enable-fragment core/yocto/sstate-mirror-cdn
```

Il server di equivalenza hash richiede il modulo Python websockets versione 9.1 o successiva. Debian GNU/Linux 12 (Bookworm) e versioni successive, Fedora, CentOS Stream 9 e versioni successive e Ubuntu 22.04 (LTS) e versioni successive dispongono tutte di un pacchetto sufficientemente recente. Le altre distribuzioni supportate devono ottenere il modulo da una fonte diversa dal proprio feed di pacchetti, ad esempio tramite `pip`. In alternativa, è possibile installare un tarball di *Buildtools* seguendo le istruzioni nella sezione *Versioni richieste di Git, tar, Python, make e gcc* del Manuale di Riferimento di Yocto Project.

3. **Avvio della Build:** Continuare col seguente comando per creare un'immagine del sistema operativo per il target, che in questo esempio è `core-image-sato`:

```
$ bitbake core-image-sato
```

Per informazioni sull'utilizzo del comando `bitbake`, consulta la sezione *BitBake* nel Manuale Introduttivo e Concetti di Yocto Project, oppure consultare *The BitBake Command* nel Manuale Utente di BitBake.

4. **Simulare l'Immagine con QEMU:** Una volta creata questa immagine, si può avviare QEMU, un "Quick EMUlator" incluso nello Yocto Project:

```
$ runqemu qemux86-64
```

Per ulteriori informazioni sull'esecuzione di QEMU, consultare il capitolo *Using the Quick EMUlator (QEMU)* nel Manuale di Sviluppo dei Task di Yocto Project.

5. **Uscita da QEMU:** Per uscire da QEMU, cliccare sull'icona di spegnimento oppure digitare `Ctrl-C` nella finestra di trascrizione di QEMU da cui è stato avviato il programma.

## 8.11 Using Quilt in Your Workflow

*Quilt* is a powerful tool that allows you to capture source code changes without having a clean source tree. This section outlines the typical workflow you can use to modify source code, test changes, and then preserve the changes in the form of a patch all using *Quilt*.

 **Nota**

With regard to preserving changes to source files, if you clean a recipe or have *rm\_work* enabled, the *devtool workflow* as described in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual is a safer development flow than the flow that uses *Quilt*.

Follow these general steps:

1. *Find the Source Code*: Temporary source code used by the OpenEmbedded build system is kept in the [Build Directory](#). See the "[Finding Temporary Source Code](#)" section to learn how to locate the directory that has the temporary source code for a particular package.
2. *Change Your Working Directory*: You need to be in the directory that has the temporary source code. That directory is defined by the `S` variable.
3. *Create a New Patch*: Before modifying source code, you need to create a new patch. To create a new patch file, use `quilt new` as below:

```
$ quilt new my_changes.patch
```

4. *Notify Quilt and Add Files*: After creating the patch, you need to notify Quilt about the files you plan to edit. You notify Quilt by adding the files to the patch you just created:

```
$ quilt add file1.c file2.c file3.c
```

5. *Edit the Files*: Make your changes in the source code to the files you added to the patch.
6. *Test Your Changes*: Once you have modified the source code, the easiest way to test your changes is by calling the `do_compile` task as shown in the following example:

```
$ bitbake -c compile -f package
```

The `-f` or `--force` option forces the specified task to execute. If you find problems with your code, you can just keep editing and re-testing iteratively until things work as expected.

#### Nota

All the modifications you make to the temporary source code disappear once you run the `do_clean` or `do_cleanall` tasks using BitBake (i.e. `bitbake -c clean package` and `bitbake -c cleanall package`). Modifications will also disappear if you use the `rm_work` feature as described in the "[Conserving Disk Space During Builds](#)" section.

7. *Generate the Patch*: Once your changes work as expected, you need to use Quilt to generate the final patch that contains all your modifications:

```
$ quilt refresh
```

At this point, the `my_changes.patch` file has all your edits made to the `file1.c`, `file2.c`, and `file3.c` files.

You can find the resulting patch file in the `patches/` subdirectory of the source (`S`) directory.

8. *Copy the Patch File*: For simplicity, copy the patch file into a directory named `files`, which you can create in the same directory that holds the recipe (`.bb`) file or the append (`.bbappend`) file. Placing the patch here guarantees that the OpenEmbedded build system will find the patch. Next, add the patch into the `SRC_URI` of the recipe. Here is an example:

```
SRC_URI += "file://my_changes.patch"
```

## 8.12 Using a Development Shell

When debugging certain commands or even when just editing packages, `devshell` can be a useful tool. When you invoke `devshell`, all tasks up to and including `do_patch` are run for the specified target. Then, a new terminal is opened and you are placed in `${S}`, the source directory. In the new terminal, all the OpenEmbedded build-related environment variables are still defined so you can use commands such as `configure` and `make`. The commands execute just as if the OpenEmbedded build system were executing them. Consequently, working this way can be helpful when debugging a build or preparing software to be used with the OpenEmbedded build system.

Here is an example that uses `devshell` on a target named `matchbox-desktop`:

```
$ bitbake matchbox-desktop -c devshell
```

This command spawns a terminal with a shell prompt within the OpenEmbedded build environment. The `OE_TERMINAL` variable controls what type of shell is opened.

For spawned terminals, the following occurs:

- The `PATH` variable includes the cross-toolchain.
- The `pkgconfig` variables find the correct `.pc` files.
- The `configure` command finds the Yocto Project site files as well as any other necessary files.

Within this environment, you can run `configure` or `compile` commands as if they were being run by the OpenEmbedded build system itself. As noted earlier, the working directory also automatically changes to the Source Directory (`S`).

To manually run a specific task using `devshell`, run the corresponding `run.*` script in the `${WORKDIR}/temp` directory (e.g., `run.do_configure.pid`). If a task's script does not exist, which would be the case if the task was skipped by way of the `sstate` cache, you can create the task by first running it outside of the `devshell`:

```
$ bitbake -c task
```

### Nota

- Execution of a task's `run.*` script and BitBake's execution of a task are identical. In other words, running the script re-runs the task just as it would be run using the `bitbake -c` command.
- Any `run.*` file that does not have a `.pid` extension is a symbolic link (symlink) to the most recent version of that file.

Remember, that the `devshell` is a mechanism that allows you to get into the BitBake task execution environment. And as such, all commands must be called just as BitBake would call them. That means you need to provide the appropriate options for cross-compilation and so forth as applicable.

When you are finished using `devshell`, exit the shell or close the terminal window.

**i Nota**

- It is worth remembering that when using `devshell` you need to use the full compiler name such as `arm-poky-linux-gnueabi-gcc` instead of just using `gcc`. The same applies to other applications such as `binutils`, `libtool` and so forth. BitBake sets up environment variables such as `CC` to assist applications, such as `make` to find the correct tools.
- It is also worth noting that `devshell` still works over X11 forwarding and similar situations.

## 8.13 Using a Python Development Shell

Similar to working within a development shell as described in the previous section, you can also spawn and work within an interactive Python development shell. When debugging certain commands or even when just editing packages, `pydevshell` can be a useful tool. When you invoke the `pydevshell` task, all tasks up to and including `do_patch` are run for the specified target. Then a new terminal is opened. Additionally, key Python objects and code are available in the same way they are to BitBake tasks, in particular, the data store 'd'. So, commands such as the following are useful when exploring the data store and running functions:

```
pydevshell> d.getVar("STAGING_DIR")
'/media/build1/bitbake-builds/build/tmp/sysroots'
pydevshell> d.getVar("STAGING_DIR", False)
'${TMPDIR}/sysroots'
pydevshell> d.setVar("FOO", "bar")
pydevshell> d.getVar("FOO")
'bar'
pydevshell> d.delVar("FOO")
pydevshell> d.getVar("FOO")
pydevshell> bb.build.exec_func("do_unpack", d)
pydevshell>
```

See the "Functions You Can Call From Within Python" section in the BitBake User Manual for details about available functions.

The commands execute just as if the OpenEmbedded build system were executing them. Consequently, working this way can be helpful when debugging a build or preparing software to be used with the OpenEmbedded build system.

Here is an example that uses `pydevshell` on a target named `matchbox-desktop`:

```
$ bitbake matchbox-desktop -c pydevshell
```

This command spawns a terminal and places you in an interactive Python interpreter within the OpenEmbedded build environment. The `OE_TERMINAL` variable controls what type of shell is opened.

When you are finished using `pydevshell`, you can exit the shell either by using `Ctrl+d` or closing the terminal window.

## 8.14 Building

This section describes various build procedures, such as the steps needed for a simple build, building a target for multiple configurations, generating an image for more than one machine, and so forth.

### 8.14.1 Building a Simple Image


In the development environment, you need to build an image whenever you change hardware support, add or change system libraries, or add or change services that have dependencies. There are several methods that allow you to build an image within the Yocto Project. This section presents the basic steps you need to build a simple image using BitBake from a build host running Linux.

#### **i** Nota

- For information on how to build an image using *Toaster*, see the *Manuale Utente di Toaster*.
- For information on how to use `devtool` to build images, see the "Using `devtool` in Your SDK Workflow" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.
- For a quick example on how to build an image using the OpenEmbedded build system, see the *Build Rapida di un'Immagine con lo Yocto Project* document.
- You can also use the [Yocto Project BitBake](#) extension for Visual Studio Code to build images.

The build process creates an entire Linux distribution from source and places it in your *Build Directory* under `tmp/` `deploy/images`. For detailed information on the build process using BitBake, see the "Immagini" section in the Yocto Project Overview and Concepts Manual.

The following figure and list overviews the build process:



1. *Set up Your Host Development System to Support Development Using the Yocto Project:* See the "[Setting Up to Use the Yocto Project](#)" section for options on how to get a build host ready to use the Yocto Project.
2. *Make Sure Your Configuration is Correct:* Use `bitbake-config-build` to define the `MACHINE` or `DISTRO`, and open your `build/conf/site.conf` file to set site-specific settings.
3. *Build the Image:* Build the image using the `bitbake` command:

```
$ bitbake target
```

#### Nota

For information on BitBake, see the [BitBake User Manual](#).

The target is the name of the recipe you want to build. Common targets are the images in `meta/recipes-core/images`, `meta/recipes-sato/images`, and so forth all found in [OpenEmbedded-Core \(OE-Core\)](#). Alternatively, the target can be the name of a recipe for a specific piece of software such as BusyBox. For more details about the images the OpenEmbedded build system supports, see the "[Immagini](#)" chapter in the Yocto Project Reference Manual.

As an example, the following command builds the `core-image-minimal` image:

```
$ bitbake core-image-minimal
```

Once an image has been built, it often needs to be installed. The images and kernels built by the OpenEmbedded build system are placed in the [Build Directory](#) in `tmp/deploy/images`. For information on how to run pre-built images such as `qemux86` and `qemuarm`, see the [Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit \(SDK/eSDK\)](#) manual. For information about how to install these images, see the documentation for your particular board or machine.

## 8.14.2 Building Images for Multiple Targets Using Multiple Configurations

See the [Building Images for Multiple Targets With Multiconfig](#) section of the Yocto Project Development Tasks Manual.

## 8.14.3 Building an Initial RAM Filesystem (Initramfs) Image

An initial RAM filesystem ([Initramfs](#)) image provides a temporary root filesystem used for early system initialization, typically providing tools and loading modules needed to locate and mount the final root filesystem.

Follow these steps to create an [Initramfs](#) image:

1. *Create the Initramfs Image Recipe:* You can reference the `core-image-minimal-initramfs.bb` recipe found in the `meta/recipes-core` directory in [OpenEmbedded-Core \(OE-Core\)](#) as an example from which to work. The `core-image-minimal-initramfs` recipe is based on the [initramfs-framework](#) recipe described below.
2. *Decide if You Need to Bundle the Initramfs Image Into the Kernel Image:* If you want the [Initramfs](#) image that is built to be bundled in with the kernel image, set the `INITRAMFS_IMAGE_BUNDLE` variable to "1" in a [configuration file](#), such as a machine [configuration file](#), and set the `INITRAMFS_IMAGE` variable in the recipe that builds the kernel image.



Setting the `INITRAMFS_IMAGE_BUNDLE` flag causes the `Initramfs` image to be unpacked into the `${B}/usr/` directory. The unpacked `Initramfs` image is then passed to the kernel's `Makefile` using the `CONFIG_INITRAMFS_SOURCE` variable, allowing the `Initramfs` image to be built into the kernel normally.

3. *Optionally Add Items to the Initramfs Image Through the Initramfs Image Recipe:* If you add items to the `Initramfs` image by way of its recipe, you should use `PACKAGE_INSTALL` rather than `IMAGE_INSTALL`. `PACKAGE_INSTALL` gives more direct control of what is added to the image as compared to the defaults you might not necessarily want that are set by the `image` or `core-image` classes.
4. *Build the Kernel Image and the Initramfs Image:* Build your kernel image using BitBake. Because the `Initramfs` image recipe is a dependency of the kernel image, the `Initramfs` image is built as well and bundled with the kernel image if you used the `INITRAMFS_IMAGE_BUNDLE` variable described earlier.

### Customizing an Initramfs using `initramfs-framework`

The `core-image-minimal-initramfs.bb` recipe found in `meta/recipes-core/images` uses the `initramfs-framework_1.0.bb` recipe as its base component. The goal of the `initramfs-framework` recipe is to provide the building blocks to build a customized `Initramfs`.

The `initramfs-framework` recipe relies on shell initialization scripts defined in `meta/recipes-core/initrdscripts/initramfs-framework`. Since some of these scripts do not apply for all use cases, the `initramfs-framework` recipe defines different packages:

- `initramfs-framework-base`: this package installs the basic components of an `Initramfs`, such as the `init` script or the `/dev/console` character special file. As this package is a runtime dependency of all modules listed below, it is automatically pulled in when one of the modules is installed in the image.
- `initramfs-module-exec`: support for execution of applications.
- `initramfs-module-mdev`: support for `mdev`.
- `initramfs-module-udev`: support for `Udev`.
- `initramfs-module-e2fs`: support for `ext4/ext3/ext2` filesystems.
- `initramfs-module-nfsrootfs`: support for locating and mounting the root partition via `NFS`.
- `initramfs-module-rootfs`: support for locating and mounting the root partition.
- `initramfs-module-debug`: dynamic debug support.
- `initramfs-module-lvm`: `LVM` rootfs support.
- `initramfs-module-overlayroot`: support for mounting a read-write overlay on top of a read-only root filesystem.

In addition to the packages defined by the `initramfs-framework` recipe itself, the following packages are defined by the recipes present in `meta/recipes-core/initrdscripts`:

- `initramfs-module-install`: module to create and install a partition layout on a selected block device.
- `initramfs-module-install-efi`: module to create and install an EFI partition layout on a selected block device.
- `initramfs-module-setup-live`: module to start a shell in the `Initramfs` if `root=/dev/ram0` is passed in the `Kernel command-line` or the `root=` parameter was not passed.

To customize the *Initramfs*, you can add or remove packages listed earlier from the *PACKAGE\_INSTALL* variable with a *bbappend* on the *core-image-minimal-initramfs* recipe, or create a custom recipe for the *Initramfs* taking *core-image-minimal-initramfs* as example.

Custom scripts can be added to the *Initramfs* by writing your own recipes. The recipes are conventionally named *initramfs-module-<module name>* where *<module name>* is the name of the module. The recipe should set its *RDEPENDS* package-specific variables to include *initramfs-framework-base* and the other packages on which the module depends at runtime.

The recipe must install shell initialization scripts in */\${D}/init.d* and must follow the *<number>-<script name>* naming scheme where:

- *<number>* is a *two-digit* number that affects the execution order of the script compared to others. For example, the script *80-setup-live* would be executed after *01-udev* because 80 is greater than 01.

This number being two-digits is important here as the scripts are executed alphabetically. For example, the script *10-script* would be executed before the script *8-script*, because 1 is inferior to 8. Therefore, the script should be named *08-script*.

- *<script name>* is the script name which you can choose freely.

If two script use the same *<number>*, they are sorted alphabetically based on *<script name>*.

## Bundling an Initramfs Image From a Separate Multiconfig

There may be a case where we want to build an *Initramfs* image which does not inherit the same distro policy as our main image, for example, we may want our main image to use *TCLIBC = "glibc"*, but to use *TCLIBC = "musl"* in our *Initramfs* image to keep a smaller footprint. However, by performing the steps mentioned above the *Initramfs* image will inherit *TCLIBC = "glibc"* without allowing us to override it.

To achieve this, you need to perform some additional steps:

1. *Create a multiconfig for your Initramfs image:* You can perform the steps on "*Building Images for Multiple Targets Using Multiple Configurations*" to create a separate multiconfig. For the sake of simplicity let's assume such multiconfig is called: *initramfscfg.conf* and contains the variables:

```
TMPDIR = "${TOPDIR}/tmp-initramfscfg"
TCLIBC = "musl"
```

2. *Set additional Initramfs variables on your main configuration:* Additionally, in your *configuration file* you need to set the variables:

```
INITRAMFS_MULTICONFIG = "initramfscfg"
INITRAMFS_DEPLOY_DIR_IMAGE = "${TOPDIR}/tmp-initramfscfg/deploy/images/$
↪ {MACHINE}"
```

The variables *INITRAMFS\_MULTICONFIG* and *INITRAMFS\_DEPLOY\_DIR\_IMAGE* are used to create a multiconfig dependency from the kernel to the *INITRAMFS\_IMAGE* to be built coming from the *initramfscfg* multiconfig, and to let the buildsysteem know where the *INITRAMFS\_IMAGE* will be located.

Building a system with such configuration will build the kernel using the main configuration but the *do\_bundle\_initramfs* task will grab the selected *INITRAMFS\_IMAGE* from *INI-*

`TRAMFS_DEPLOY_DIR_IMAGE` instead, resulting in a musl based *Initramfs* image bundled in the kernel but a glibc based main image.

The same is applicable to avoid inheriting `DISTRO_FEATURES` on `INITRAMFS_IMAGE` or to build a different `DISTRO` for it such as `poky-tiny`.

### 8.14.4 Building a Tiny System

Very small distributions have some significant advantages such as requiring less on-die or in-package memory (cheaper), better performance through efficient cache usage, lower power requirements due to less memory, faster boot times, and reduced development overhead. Some real-world examples where a very small distribution gives you distinct advantages are digital cameras, medical devices, and small headless systems.

This section presents information that shows you how you can trim your distribution to even smaller sizes than the `poky-tiny` distribution, which is around 5 Mbytes, that can be built out-of-the-box using the Yocto Project.

#### Tiny System Overview

The following list presents the overall steps you need to consider and perform to create distributions with smaller root filesystems, achieve faster boot times, maintain your critical functionality, and avoid initial RAM disks:

- *Determine your goals and guiding principles*
- *Understand What Contributes to Your Image Size*
- *Reduce the size of the root filesystem*
- *Reduce the size of the kernel*
- *Remove Package Management Requirements*
- *Look for Other Ways to Minimize Size*
- *Iterate on the Process*

#### Goals and Guiding Principles

Before you can reach your destination, you need to know where you are going. Here is an example list that you can use as a guide when creating very small distributions:

- Determine how much space you need (e.g. a kernel that is 1 Mbyte or less and a root filesystem that is 3 Mbytes or less).
- Find the areas that are currently taking 90% of the space and concentrate on reducing those areas.
- Do not create any difficult "hacks" to achieve your goals.
- Leverage the device-specific options.
- Work in a separate layer so that you keep changes isolated. For information on how to create layers, see the "*Comprendere e Creare i Layer*" section.

## Understand What Contributes to Your Image Size

It is easiest to have something to start with when creating your own distribution. You can use the Yocto Project out-of-the-box to create the `poky-tiny` distribution. Ultimately, you will want to make changes in your own distribution that are likely modeled after `poky-tiny`.

### Nota

To use `poky-tiny` in your build, set the *distro/* fragment to "poky-tiny" as described in the *bitbake-config-build enable-fragment* section, or set the *DISTRO* variable to "poky-tiny" in the *build/conf/local.conf* file.

Understanding some memory concepts will help you reduce the system size. Memory consists of static, dynamic, and temporary memory. Static memory is the TEXT (code), DATA (initialized data in the code), and BSS (uninitialized data) sections. Dynamic memory represents memory that is allocated at runtime: stacks, hash tables, and so forth. Temporary memory is recovered after the boot process. This memory consists of memory used for decompressing the kernel and for the `__init__` functions.

To help you see where you currently are with kernel and root filesystem sizes, you can use two tools found in *OpenEmbedded-Core (OE-Core)* in the `scripts/tiny/` directory:

- `ksize.py`: Reports component sizes for the kernel build objects.
- `dirsize.py`: Reports component sizes for the root filesystem.

This next tool and command help you organize configuration fragments and view file dependencies in a human-readable form:

- `merge_config.sh`: Helps you manage configuration files and fragments within the kernel. With this tool, you can merge individual configuration fragments together. The tool allows you to make overrides and warns you of any missing configuration options. The tool is ideal for allowing you to iterate on configurations, create minimal configurations, and create configuration files for different machines without having to duplicate your process.

The `merge_config.sh` script is part of the Linux Yocto kernel Git repositories (i.e. `linux-yocto-3.14`, `linux-yocto-3.10`, `linux-yocto-3.8`, and so forth) in the `scripts/kconfig` directory.

For more information on configuration fragments, see the "*Creating Configuration Fragments*" section in the Yocto Project Linux Kernel Development Manual.

- `bitbake -u taskexp -g bitbake_target`: Using the BitBake command with these options brings up a Dependency Explorer from which you can view file dependencies. Understanding these dependencies allows you to make informed decisions when cutting out various pieces of the kernel and root filesystem.

## Trim the Root Filesystem

The root filesystem is made up of packages for booting, libraries, and applications. To change things, you can configure how the packaging happens, which changes the way you build them. You can also modify the filesystem itself or select a different filesystem.

First, find out what is hogging your root filesystem by running the `dirsize.py` script from your root directory:

```
$ cd root-directory-of-image
$ dirsize.py 100000 > dirsize-100k.log
$ cat dirsize-100k.log
```

You can apply a filter to the script to ignore files under a certain size. The previous example filters out any files below 100 Kbytes. The sizes reported by the tool are uncompressed, and thus will be smaller by a relatively constant factor in a compressed root filesystem. When you examine your log file, you can focus on areas of the root filesystem that take up large amounts of memory.

You need to be sure that what you eliminate does not cripple the functionality you need. One way to see how packages relate to each other is by using the Dependency Explorer UI with the BitBake command:

```
$ cd image-directory
$ bitbake -u taskexp -g image
```

Use the interface to select potential packages you wish to eliminate and see their dependency relationships.

When deciding how to reduce the size, get rid of packages that result in minimal impact on the feature set. For example, you might not need a VGA display. Or, you might be able to get by with `devtmpfs` and `mdev` instead of `udev`.

Use your distro *configuration file* to make such changes. For example, to eliminate `udev` and `glib`, set the following:

```
VIRTUAL-RUNTIME_dev_manager = ""
```

Finally, you should consider exactly the type of root filesystem you need to meet your needs while also reducing its size. For example, consider `cramfs`, `squashfs`, `ubifs`, `ext2`, or an *initramfs* using `initramfs`. Be aware that `ext3` requires a 1 Mbyte journal. If you are okay with running read-only, you do not need this journal.

#### Nota

After each round of elimination, you need to rebuild your system and then use the tools to see the effects of your reductions.

## Trim the Kernel

The kernel is built by including policies for hardware-independent aspects. What subsystems do you enable? For what architecture are you building? Which drivers do you build by default?

#### Nota

You can modify the kernel source if you want to help with boot time.

Run the `ksize.py` script from the top-level Linux build directory to get an idea of what is making up the kernel:

```
$ cd top-level-linux-build-directory
$ ksize.py > ksize.log
$ cat ksize.log
```

When you examine the log, you will see how much space is taken up with the built-in `.o` files for drivers, networking, core kernel files, filesystem, sound, and so forth. The sizes reported by the tool are uncompressed, and thus will be smaller by a relatively constant factor in a compressed kernel image. Look to reduce the areas that are large and taking up around the "90% rule."

To examine, or drill down, into any particular area, use the `-d` option with the script:

```
$ ksize.py -d > ksize.log
```

Using this option breaks out the individual file information for each area of the kernel (e.g. drivers, networking, and so forth).

Use your log file to see what you can eliminate from the kernel based on features you can let go. For example, if you are not going to need sound, you do not need any drivers that support sound.

After figuring out what to eliminate, you need to reconfigure the kernel to reflect those changes during the next build. You could run `menuconfig` and make all your changes at once. However, that makes it difficult to see the effects of your individual eliminations and also makes it difficult to replicate the changes for perhaps another target device. A better method is to start with no configurations using `allnoconfig`, create configuration fragments for individual changes, and then manage the fragments into a single configuration file using `merge_config.sh`. The tool makes it easy for you to iterate using the configuration change and build cycle.

Each time you make configuration changes, you need to rebuild the kernel and check to see what impact your changes had on the overall size.

## Remove Package Management Requirements

Packaging requirements add size to the image. One way to reduce the size of the image is to remove all the packaging requirements from the image. This reduction includes both removing the package manager and its unique dependencies as well as removing the package management data itself.

To eliminate all the packaging requirements for an image, be sure that "package-management" is not part of your *IMAGE\_FEATURES* statement for the image. When you remove this feature, you are removing the package manager as well as its dependencies from the root filesystem.

## Look for Other Ways to Minimize Size

Depending on your particular circumstances, other areas that you can trim likely exist. The key to finding these areas is through tools and methods described here combined with experimentation and iteration. Here are a couple of areas to experiment with:

- `glibc`: In general, follow this process:
  1. Remove `glibc` features from *DISTRO\_FEATURES* that you think you do not need.
  2. Build your distribution.

3. If the build fails due to missing symbols in a package, determine if you can reconfigure the package to not need those features. For example, change the configuration to not support wide character support as is done for `ncurses`. Or, if support for those characters is needed, determine what `glibc` features provide the support and restore the configuration.
  4. Rebuild and repeat the process.
- `busybox`: For BusyBox, use a process similar as described for `glibc`. A difference is you will need to boot the resulting system to see if you are able to do everything you expect from the running system. You need to be sure to integrate configuration fragments into Busybox because BusyBox handles its own core features and then allows you to add configuration fragments on top.

### Iterate on the Process

If you have not reached your goals on system size, you need to iterate on the process. The process is the same. Use the tools and see just what is taking up 90% of the root filesystem and the kernel. Decide what you can eliminate without limiting your device beyond what you need.

Depending on your system, a good place to look might be Busybox, which provides a stripped down version of Unix tools in a single, executable file. You might be able to drop virtual terminal services or perhaps `ipv6`.

## 8.14.5 Building Images for More than One Machine

A common scenario developers face is creating images for several different machines that use the same software environment. In this situation, it is tempting to set the tunings and optimization flags for each build specifically for the targeted hardware (i.e. "maxing out" the tunings). Doing so can considerably add to build times and package feed maintenance collectively for the machines. For example, selecting tunes that are extremely specific to a CPU core used in a system might enable some micro optimizations in GCC for that particular system but would otherwise not gain you much of a performance difference across the other systems as compared to using a more general tuning across all the builds (e.g. setting `DEFAULTTUNE` specifically for each machine's build). Rather than "max out" each build's tunings, you can take steps that cause the OpenEmbedded build system to reuse software across the various machines where it makes sense.

If build speed and package feed maintenance are considerations, you should consider the points in this section that can help you optimize your tunings to best consider build times and package feed maintenance.

- *Share the Build Directory* : If at all possible, share the `TMPDIR` across builds. The Yocto Project supports switching between different `MACHINE` values in the same `TMPDIR`. This practice is well supported and regularly used by developers when building for multiple machines. When you use the same `TMPDIR` for multiple machine builds, the OpenEmbedded build system can reuse the existing native and often cross-recipes for multiple machines. Thus, build time decreases.

**i Nota**

If *DISTRO* settings change or fundamental configuration settings such as the filesystem layout, you need to work with a clean *TMPDIR*. Sharing *TMPDIR* under these circumstances might work but since it is not guaranteed, you should use a clean *TMPDIR*.

- *Enable the Appropriate Package Architecture:* By default, the OpenEmbedded build system enables three levels of package architectures: "all", "tune" or "package", and "machine". Any given recipe usually selects one of these package architectures (types) for its output. Depending for what a given recipe creates packages, making sure you enable the appropriate package architecture can directly impact the build time.

A recipe that just generates scripts can enable "all" architecture because there are no binaries to build. To specifically enable "all" architecture, be sure your recipe inherits the *allarch* class. This class is useful for "all" architectures because it configures many variables so packages can be used across multiple architectures.

If your recipe needs to generate packages that are machine-specific or when one of the build or runtime dependencies is already machine-architecture dependent, which makes your recipe also machine-architecture dependent, make sure your recipe enables the "machine" package architecture through the *MACHINE\_ARCH* variable:

```
PACKAGE_ARCH = "${MACHINE_ARCH}"
```

When you do not specifically enable a package architecture through the *PACKAGE\_ARCH*, The OpenEmbedded build system defaults to the *TUNE\_PKGARCH* setting:

```
PACKAGE_ARCH = "${TUNE_PKGARCH}"
```

- *Choose a Generic Tuning File if Possible:* Some tunes are more generic and can run on multiple targets (e.g. an *armv5* set of packages could run on *armv6* and *armv7* processors in most cases). Similarly, *i486* binaries could work on *i586* and higher processors. You should realize, however, that advances on newer processor versions would not be used.

If you select the same tune for several different machines, the OpenEmbedded build system reuses software previously built, thus speeding up the overall build time. Realize that even though a new sysroot for each machine is generated, the software is not recompiled and only one package feed exists.

- *Manage Granular Level Packaging:* Sometimes there are cases where injecting another level of package architecture beyond the three higher levels noted earlier can be useful. For example, consider how NXP (formerly Freescale) allows for the easy reuse of binary packages in their layer *meta-freescale*. In this example, the *fsl-dynamic-packagearch* class shares GPU packages for i.MX53 boards because all boards share the AMD GPU. The i.MX6-based boards can do the same because all boards share the Vivante GPU. This class inspects the BitBake datastore to identify if the package provides or depends on one of the sub-architecture values. If so, the class sets the *PACKAGE\_ARCH* value based on the *MACHINE\_SUBARCH* value. If the package does not provide or depend on one of the sub-architecture values but it matches a value in the machine-specific filter, it sets *MACHINE\_ARCH*. This behavior reduces the number of packages built and saves build time by reusing binaries.



- *Use Tools to Debug Issues:* Sometimes you can run into situations where software is being rebuilt when you think it should not be. For example, the OpenEmbedded build system might not be using shared state between machines when you think it should be. These types of situations are usually due to references to machine-specific variables such as `MACHINE`, `SERIAL_CONSOLES`, `XSERVER`, `MACHINE_FEATURES`, and so forth in code that is supposed to only be tune-specific or when the recipe depends (`DEPENDS`, `RDEPENDS`, `RRECOMMENDS`, `RSUGGESTS`, and so forth) on some other recipe that already has `PACKAGE_ARCH` defined as `"${MACHINE_ARCH}"`.

#### Nota

Patches to fix any issues identified are most welcome as these issues occasionally do occur.

For such cases, you can use some tools to help you sort out the situation:

- `state-diff-machines.sh``*:*` You can find this tool in the ```scripts` directory of the Source Repositories. See the comments in the script for information on how to use the tool.
- *BitBake's "-S printdiff" Option:* Using this option causes BitBake to try to establish the most recent signature match (e.g. in the shared state cache) and then compare matched signatures to determine the stamps and delta where these two stamp trees diverge.

### 8.14.6 Building Software from an External Source

By default, the OpenEmbedded build system uses the *Build Directory* when building source code. The build process involves fetching the source files, unpacking them, and then patching them if necessary before the build takes place.

There are situations where you might want to build software from source files that are external to and thus outside of the OpenEmbedded build system. For example, suppose you have a project that includes a new BSP with a heavily customized kernel. And, you want to minimize exposing the build system to the development team so that they can focus on their project and maintain everyone's workflow as much as possible. In this case, you want a kernel source directory on the development machine where the development occurs. You want the recipe's `SRC_URI` variable to point to the external directory and use it as is, not copy it.

To build from software that comes from an external source, all you need to do is inherit the *externalsrc* class and then set the `EXTERNALSRC` variable to point to your external source code. Here are the statements to put in your *build/conf/local.conf* file:

```
INHERIT += "externalsrc"
EXTERNALSRC:pn-myrecipe = "path-to-your-source-tree"
```

This next example shows how to accomplish the same thing by setting `EXTERNALSRC` in the recipe itself or in the recipe's append file:

```
EXTERNALSRC = "path"
EXTERNALSRC_BUILD = "path"
```

**i Nota**

In order for these settings to take effect, you must globally or locally inherit the *externalsrc* class.

By default, *externalsrc* builds the source code in a directory separate from the external source directory as specified by *EXTERNALSRC*. If you need to have the source built in the same directory in which it resides, or some other nominated directory, you can set *EXTERNALSRC\_BUILD* to point to that directory:

```
EXTERNALSRC_BUILD:pn-myrecipe = "path-to-your-source-tree"
```

**i Nota**

The values of *EXTERNALSRC* and *EXTERNALSRC\_BUILD* must be absolute paths.

### 8.14.7 Replicating a Build Offline

It can be useful to take a "snapshot" of upstream sources used in a build and then use that "snapshot" later to replicate the build offline. To do so, you need to first prepare and populate your downloads directory with your "snapshot" of files. Once your downloads directory is ready, you can use it at any time and from any machine to replicate your build.

Follow these steps to populate your Downloads directory:

1. *Create a Clean Downloads Directory:* Start with an empty downloads directory (*DL\_DIR*). You start with an empty downloads directory by either removing the files in the existing directory or by setting *DL\_DIR* to point to either an empty location or one that does not yet exist.
2. *Generate Tarballs of the Source Git Repositories:* Edit your *build/conf/local.conf* configuration file as follows:

```
DL_DIR = "/home/your-download-dir/"  
BB_GENERATE_MIRROR_TARBALLS = "1"
```

During the fetch process in the next step, BitBake gathers the source files and creates tarballs in the directory pointed to by *DL\_DIR*. See the *BB\_GENERATE\_MIRROR\_TARBALLS* variable for more information.

3. *Populate Your Downloads Directory Without Building:* Use BitBake to fetch your sources but inhibit the build:

```
$ bitbake target --runall=fetch
```

The downloads directory (i.e. *\${DL\_DIR}*) now has a "snapshot" of the source files in the form of tarballs, which can be used for the build.

4. *Optionally Remove Any Git or other SCM Subdirectories From the Downloads Directory:* If you want, you can clean up your downloads directory by removing any Git or other Source Control Management (SCM) subdirectories such as *\${DL\_DIR}/git2/\**. The tarballs already contain these subdirectories.

Once your downloads directory has everything it needs regarding source files, you can create your "own-mirror" and build your target. Understand that you can use the files to build the target offline from any machine and at any time.

Follow these steps to build your target using the files in the downloads directory:

1. *Using Local Files Only:* Inside your *build/conf/local.conf* or distro *configuration file*, add the *SOURCE\_MIRROR\_URL* variable, inherit the *own-mirrors* class, and add the *BB\_NO\_NETWORK* variable:

```
SOURCE_MIRROR_URL ?= "file:///home/your-download-dir/"
INHERIT += "own-mirrors"
BB_NO_NETWORK = "1"
```

The *SOURCE\_MIRROR\_URL* and *own-mirrors* class set up the system to use the downloads directory as your "own mirror". Using the *BB\_NO\_NETWORK* variable makes sure that BitBake's fetching process in step 3 stays local, which means files from your "own-mirror" are used.

2. *Start With a Clean Build:* You can start with a clean build by removing the `${TMPDIR}` directory or using a new *Build Directory*.
3. *Build Your Target:* Use BitBake to build your target:

```
$ bitbake target
```

The build completes using the known local "snapshot" of source files from your mirror. The resulting tarballs for your "snapshot" of source files are in the downloads directory.

#### Nota

The offline build does not work if recipes attempt to find the latest version of software by setting *SRCREV* to `${AUTOREV}`:

```
SRCREV = "${AUTOREV}"
```

When a recipe sets *SRCREV* to `${AUTOREV}`, the build system accesses the network in an attempt to determine the latest version of software from the SCM. Typically, recipes that use *AUTOREV* are custom or modified recipes. Recipes that reside in public repositories usually do not use *AUTOREV*.

If you do have recipes that use *AUTOREV*, you can take steps to still use the recipes in an offline build. Do the following:

1. Use a configuration generated by enabling *build history*.
2. Use the `buildhistory-collect-srcrevs` command to collect the stored *SRCREV* values from the build's history. For more information on collecting these values, see the "*Build History Package Information*" section.
3. Once you have the correct source revisions, you can modify those recipes to set *SRCREV* to specific versions of the software.

## 8.15 Building Images for Multiple Targets With Multiconfig

You can use a single `bitbake` command to build multiple images or packages for different targets where each image or package requires a different configuration (multiple configuration builds). The builds, in this scenario, are sometimes referred to as "multiconfigs", and this section uses that term throughout.

This section describes how to set up for multiple configuration builds and how to account for cross-build dependencies between the multiconfigs.

### 8.15.1 Setting Up and Running a Multiple Configuration Build

To accomplish a multiple configuration build, you must define each target's configuration separately using a parallel *configuration file* in the *Build Directory* or configuration directory within a layer, and you must follow a required file hierarchy. Additionally, you must enable the multiple configuration builds in your *build/conf/local.conf* file.

Follow these steps to set up and execute multiple configuration builds:

- *Create Separate Configuration Files:* You need to create a single *Configuration File* for each build target (each multiconfig). The configuration definitions are implementation dependent but often each configuration file will define the *MACHINE* and the temporary directory (*TMPDIR*) BitBake uses for the build.


#### **Nota**

Whether the same temporary directory (*TMPDIR*) can be shared will depend on what is similar and what is different between the configurations. Multiple *MACHINE* targets can share the same *TMPDIR* as long as the rest of the configuration is the same, multiple *DISTRO* settings would need separate *TMPDIR* directories.

For example, consider a scenario with two different multiconfigs for the same *MACHINE*: "qemux86" built for two distributions such as "poky" and "poky-lsb". In this case, you would need to use two different *TMPDIR*.

In the general case, using separate *TMPDIR* for the different multiconfigs is strongly recommended.

The location for these multiconfig configuration files is specific. They must reside in the current *Build Directory* in a sub-directory of *conf* named *multiconfig* or within a *Layer's* *conf* directory under a directory named *multiconfig*. Here is an example that defines two configuration files for the "x86" and "arm" multiconfigs:



The usual *BBPATH* search path is used to locate multiconfig files in a similar way to other configuration files.

Here is an example showing the minimal statements needed in a *configuration file* named *qemux86.conf* for a *qemux86* target whose temporary build directory is *tmp-qemux86*:

```
MACHINE = "qemux86"
TMPDIR  = "-${BB_CURRENT_MC}"
```

BitBake will expand the `BB_CURRENT_MC` variable to the value of the current multiconfig in use. We append this value to `TMPDIR` so that any change on the definition of `TMPDIR` will automatically affect the value of `TMPDIR` for each multiconfig.

- *Add the BitBake Multi-configuration Variable to the Local Configuration File:* Use the `BBMULTICONFIG` variable in your `build/conf/local.conf` configuration file to specify each multiconfig. Continuing with the example from the previous figure, the `BBMULTICONFIG` variable needs to enable two multiconfigs: "x86" and "arm" by specifying each configuration file:

```
BBMULTICONFIG = "x86 arm"
```

#### **i** Nota

A "default" configuration already exists by definition. This configuration is named: "" (i.e. empty string) and is defined by the variables coming from your `build/conf/local.conf` file. Consequently, the previous example actually adds two additional configurations to your build: "arm" and "x86" along with "".

- *Launch BitBake:* Use the following BitBake command form to launch the multiple configuration build:

```
$ bitbake [mc:multiconfigname:]target [[mc:multiconfigname:]target] ... ]
```

For the example in this section, the following command applies:

```
$ bitbake mc:x86:core-image-minimal mc:arm:core-image-sato mc::core-image-base
```

The previous BitBake command builds several components:

- A `core-image-minimal` image that is configured through the `x86.conf` configuration file
- A `core-image-sato` image that is configured through the `arm.conf` configuration file
- A `core-image-base` that is configured through your `build/conf/local.conf` configuration file

**i Nota**

Support for multiple configuration builds in the Yocto Project 6.1 (Blacksail) Release does not include Shared State (sstate) optimizations. Consequently, if a build uses the same object twice in, for example, two different *TMPDIR* directories, the build either loads from an existing sstate cache for that build at the start or builds the object fresh.

### 8.15.2 Enabling Multiple Configuration Build Dependencies

Sometimes dependencies can exist between targets (multiconfigs) in a multiple configuration build. For example, suppose that in order to build a `core-image-sato` image for an "x86" multiconfig, the root filesystem of an "arm" multiconfig must exist. This dependency is essentially that the *do\_image* task in the `core-image-sato` recipe depends on the completion of the *do\_rootfs* task of the `core-image-minimal` recipe.

To enable dependencies in a multiple configuration build, you must declare the dependencies in the recipe using the following statement form:

```
task_or_package[mcdepends] = "mc:from_multiconfig:to_multiconfig:recipe_name:task_
↪on_which_to_depend"
```

To better show how to use this statement, consider the example scenario from the first paragraph of this section. The following statement needs to be added to the recipe that builds the `core-image-sato` image:

```
do_image[mcdepends] = "mc:x86:arm:core-image-minimal:do_rootfs"
```

In this example, the *from\_multiconfig* is "x86". The *to\_multiconfig* is "arm". The task on which the *do\_image* task in the recipe depends is the *do\_rootfs* task from the `core-image-minimal` recipe associated with the "arm" multiconfig.

Once you set up this dependency, you can build the "x86" multiconfig using a BitBake command as follows:

```
$ bitbake mc:x86:core-image-sato
```

This command executes all the tasks needed to create the `core-image-sato` image for the "x86" multiconfig. Because of the dependency, BitBake also executes through the *do\_rootfs* task for the "arm" multiconfig build.

Having a recipe depend on the root filesystem of another build might not seem that useful. Consider this change to the statement in the `core-image-sato` recipe:

```
do_image[mcdepends] = "mc:x86:arm:core-image-minimal:do_image"
```

In this case, BitBake must create the `core-image-minimal` image for the "arm" build since the "x86" build depends on it.

Because "x86" and "arm" are enabled for multiple configuration builds and have separate configuration files, BitBake places the artifacts for each build in the respective temporary build directories (i.e. *TMPDIR*).

### 8.15.3 Suggested best practices

- *TMPDIR* (other than the default set in *bitbake.conf*) is only set in *build/conf/local.conf* by the user. This means that we should **not** manipulate *TMPDIR* in any way within the Machine or Distro *configuration file*.
- A multiconfig should specify a *TMPDIR*, and should specify it by appending the multiconfig name with *BB\_CURRENT\_MC*.
- Recipes that are used to transfer the output from a multiconfig build to another should use `do_task[mcdepends]` to trigger the build of the component, and then transfer the item to the current configuration in *do\_install* and *do\_deploy*, assuming the value of the deployed item based on *TMPDIR*.

The *do\_install* and *do\_deploy* tasks should look like this:

```
do_install() {
    install -m 0644 ${TMPDIR}-<multiconfig>/tmp/deploy/images/<machine>/
    ↪somefile ${D}/some/path
}

do_deploy() {
    install -m 0644 ${TMPDIR}-<multiconfig>/tmp/deploy/images/<machine>/
    ↪somefile ${DEPLOYDIR}/somefile
}
```

In the example above:

- *<multiconfig>* is the multiconfig name as set by the multiconfig *configuration file* (see the *Setting Up and Running a Multiple Configuration Build* section above).
- *<machine>* must be the *MACHINE* for which *somefile* was built and deployed. This value may differ from the current *MACHINE* if the multiconfig *configuration file* overrides it.
- Firmware recipes can set the *INHIBIT\_DEFAULT\_DEPS* variable to 1 if they don't rely on default dependencies such as the standard C library.

### 8.15.4 Common use case: building baremetal firmware alongside a Linux build

A common use case for multiconfig is to use the default configuration as the regular Linux build, while one or more multiconfigs can be used to build special components, such as baremetal firmware. It would also apply to a scenario where a microcontroller, for example, is companion to a main processor where Linux is running. This section details how one can achieve these kinds of scenarios with a multiconfig build.

#### Adding a multiconfig configuration file and recipe for a baremetal firmware

As described in *Setting Up and Running a Multiple Configuration Build*, each multiconfig will require a separate *Configuration File*. In addition, we will define a separate *TMPDIR* for our baremetal firmware build configuration.

For example, we will define a new *conf/multiconfig/baremetal-firmware.conf* as follows:

```
TMPDIR .= "-${BB_CURRENT_MC}"
TCLIBC = "newlib"
```

The `baremetal-firmware.conf` file configures a separate *TMPDIR* for holding binaries compiled with the *newlib* toolchain (see *TCLIBC*).

#### Nota

Here, the default *MACHINE* is not overridden by the multiconfig configuration file. As a consequence, the architecture of the built baremetal binaries will be the same. In other cases, where the firmware runs on a completely different architecture, the *MACHINE* must be overridden.

We then create a recipe `my-firmware.bb` that defines how the baremetal firmware is built. The recipe should contain enough information for the *OpenEmbedded build system* to properly compile the firmware with our toolchain. The building tasks may vary depending on the nature of the firmware. However, the recipe should define a *deploy* task that deploys the output into the *DEPLOYDIR* directory. We will consider in the following that the file is named `my-firmware.elf`.

### Building the firmware

The firmware can be built with BitBake with the following command:

```
$ bitbake mc:baremetal-firmware:my-firmware
```

However, we would prefer for `my-firmware` to be automatically built when triggering a normal Linux build.

Using a *mcdepend*, a recipe belonging to the Linux build can trigger the build of `my-firmware`. For example, let's consider that our Linux build needs to assemble a "special" firmware that uses the output of our `my-firmware` recipe - let's call it `my-parent-firmware.bb`. Then, we should specify this dependency in `my-parent-firmware.bb` with:

```
do_compile[mcdepends] = "mc::baremetal-firmware:my-firmware:do_deploy"
```

The above will ensure that when the *do\_compile* task of `my-parent-firmware` is triggered, the *do\_deploy* task of `my-firmware` will already have run successfully.

### Using the output of `my-firmware`

After `my-firmware` recipe has deployed `my-firmware.elf`, we need to use the output in some way. We can make a series of assumptions, based on the default Yocto Project variables in order to get the binary for packaging.

First, we can set the following in `my-parent-firmware.bb`:

```
FIRMWARE_FILE ??= "${TMPDIR}-baremetal-firmware/deploy/images/<machine>/my-  
↪firmware.elf"  
FIRMWARE_FILE[vardepsexclude] += "TMPDIR"
```

The first assignment stores the value of the path to the firmware built and deployed by the `my-firmware.bb` recipe. The second assignment excludes the *TMPDIR* variable from being part of `FIRMWARE_FILE`'s dependencies --- meaning that changing the value of *TMPDIR* (for example, changing the host on which the firmware is built) will not invalidate the *shared state cache*.



Additionally, `<machine>` should be replaced by the *MACHINE* for which we are building in the baremetal-firmware context.

We can then add a *do\_install* task to `my-parent-firmware`:

```
do_install() {
    install -Dm 0644 ${FIRMWARE_FILE} ${D}/lib/firmware/my-firmware.elf
}
```

Doing the above will allow the firmware binary to be transferred and packaged into the Linux context and rootfs.

## 8.16 Speeding Up a Build

Build time can be an issue. By default, the build system uses simple controls to try and maximize build efficiency. In general, the default settings for all the following variables result in the most efficient build times when dealing with single socket systems (i.e. a single CPU). If you have multiple CPUs, you might try increasing the default values to gain more speed. See the descriptions in the glossary for each variable for more information:

- *BB\_NUMBER\_THREADS*: The maximum number of threads BitBake simultaneously executes.
- *BB\_NUMBER\_PARSE\_THREADS*: The number of threads BitBake uses during parsing.
- *PARALLEL\_MAKE*: Extra options passed to the `make` command during the *do\_compile* task in order to specify parallel compilation on the local build host.
- *PARALLEL\_MAKEINST*: Extra options passed to the `make` command during the *do\_install* task in order to specify parallel installation on the local build host.

As mentioned, these variables all scale to the number of processor cores available on the build system. For single socket systems, this auto-scaling ensures that the build system fundamentally takes advantage of potential parallel operations during the build based on the build machine's capabilities.

Additional factors that can affect build speed are:

- File system type: The file system type that the build is being performed on can also influence performance. Using `ext4` is recommended as compared to `ext2` and `ext3` due to `ext4` improved features such as extents.
- Disabling the updating of access time using `noatime`: The `noatime` mount option prevents the build system from updating file and directory access times.
- Setting a longer commit: Using the `"commit="` mount option increases the interval in seconds between disk cache writes. Changing this interval from the five second default to something longer increases the risk of data loss but decreases the need to write to the disk, thus increasing the build performance.
- Choosing the packaging backend: Of the available packaging backends, IPK is the fastest. Additionally, selecting a singular packaging backend also helps.
- Using `tmpfs` for *TMPDIR* as a temporary file system: While this can help speed up the build, the benefits are limited due to the compiler using `-pipe`. The build system goes to some lengths to avoid `sync()` calls into the file system on the principle that if there was a significant failure, the *Build Directory* contents could easily be rebuilt.

- Inheriting the `rm_work` class: Inheriting this class has shown to speed up builds due to significantly lower amounts of data stored in the data cache as well as on disk. Inheriting this class also makes cleanup of `TMP-DIR` faster, at the expense of being easily able to dive into the source code. File system maintainers have recommended that the fastest way to clean up large numbers of files is to reformat partitions rather than delete files due to the linear nature of partitions. This, of course, assumes you structure the disk partitions and file systems in a way that this is practical.

Aside from the previous list, you should keep some trade-offs in mind that can help you speed up the build:

- Remove items from `DISTRO_FEATURES` that you might not need.
- Exclude debug symbols and other debug information: If you do not need these symbols and other debug information, disabling the `*-dbg` package generation can speed up the build. You can disable this generation by setting the `INHIBIT_PACKAGE_DEBUG_SPLIT` variable to "1".
- Disable static library generation for recipes derived from `autoconf` or `libtool`: Here is an example showing how to disable static libraries and still provide an override to handle exceptions:

```
STATICLIBCONF = "--disable-static"
STATICLIBCONF:sqlite3-native = ""
EXTRA_OECONF += "${STATICLIBCONF}"
```

#### Nota

- Some recipes need static libraries in order to work correctly (e.g. `pseudo-native` needs `sqlite3-native`). Overrides, as in the previous example, account for these kinds of exceptions.
- Some packages have packaging code that assumes the presence of the static libraries. If so, you might need to exclude them as well.

## 8.17 Limiting the Host Resources Usage

While you sometimes need to *speed up a build*, you may also need to limit the resources used by the *OpenEmbedded Build System*, especially on shared infrastructures where multiple users start heavy-load builds, or when building on low-power machines.

This document aims at giving the different configuration variables available to limit the resources used by the build system. These variables should be set from a *configuration file* and thus take effect over the entire build environment. For each variable, also see the variable description in the glossary for more details.

- `BB_NUMBER_THREADS`:

This sets a hard limit on the number of threads *BitBake* can run at the same time. Lowering this value will set a limit to the number of *BitBake* threads, but will not prevent a single task from starting more compilation threads (see `PARALLEL_MAKE`).

- `BB_NUMBER_PARSE_THREADS`:

Like `BB_NUMBER_THREADS`, but this variable sets a limit on the number of threads during the parsing of the environment (before executing tasks).

- **PARALLEL\_MAKE:**

This variable should be set in the form of `-jN`, where `N` is a positive integer. This integer controls the number of threads used when starting `make`. Note that this variable is not limited to the usage of `make`, but extends to the compilation (*do\_compile* task) commands defined by the *meson*, *cmake* and such classes.

If you want to have a different limit from the rest of the build for a recipe, it is also possible to achieve with the following line added to your *build/conf/local.conf* configuration file:

```
PARALLEL_MAKE:pn-linux-yocto = "-j4"
```

The above example will limit the number of threads used by `make` for the `linux-yocto` recipe to 4.

- **PARALLEL\_MAKEINST:**

Like *PARALLEL\_MAKE*, but this variable controls the number of threads used during the *do\_install* task.

The default value of *PARALLEL\_MAKEINST* is the value of *PARALLEL\_MAKE*.

### Nota

While most of the variables in this document help to limit the CPU load, it is also possible that the host system runs out of physical RAM when running builds. This can trigger the out-of-memory killer and stop the related processes abruptly. This can create strange looking failures in the output log of the tasks in question. The out-of-memory killer only logs in the kernel `dmesg` logs, so it is advised to monitor it closely with the `dmesg` command when encountering unexpected failures during builds.

In these situations, lowering the value of *PARALLEL\_MAKE* and *BB\_NUMBER\_THREADS* is recommended.

- **BB\_PRESSURE\_MAX\_CPU, BB\_PRESSURE\_MAX\_IO and BB\_PRESSURE\_MAX\_MEMORY:**

These variables control the limit of pressure (PSI as defined by <https://docs.kernel.org/accounting/psi.html>) on the system, and will limit the number of *BitBake* threads dynamically depending on the current pressure of the system. This also means that your host must support the PSI kernel feature (otherwise see *BB\_LOADFACTOR\_MAX* below).

These variables take a positive integer between 1 (extremely low limit) and 1000000 (value unlikely ever reached). Setting an extremely low value, such as 2, is not desirable as it will result in *BitBake* limiting the number of threads to 1 most of the time.

To determine a reasonable value to set for your host, follow the steps below:

1. In a Bash shell, start the following script, which will provide an estimate of the current pressure on your host:

```
pressure="0"
while true; do
    prev_pressure="$pressure"
    pressure=$(head -1 /proc/pressure/cpu | cut -d' ' -f5 | cut -d'=' -f2)
    echo $(( $pressure - $prev_pressure ))
```

(continues on next page)

(continua dalla pagina precedente)

```
sleep 1
done
```

**Nota**

Change `/proc/pressure/cpu` to `/proc/pressure/io` or `/proc/pressure/memory` to change the pressure type to monitor.

This script can be stopped by pressing Control + C.

2. Then, start a heavy-load build, for example:

```
bitbake virtual/kernel -c compile -f
```

You can stop the build at anytime with Control + C.

3. Monitor the values printed on the console. These should indicate how the pressure evolves during the build. You can take a value below the maximum printed value as a starting point.

After setting initial values, you can monitor when the pressure exceeds of the limit set by the above variables by running *BitBake* with the `--verbose` and `--log-domains` flag:

```
$ bitbake virtual/kernel -c compile -f --verbose --log-domains BitBake.
↪RunQueue.PSI
```

In parallel, you can monitor the pressure information by tracking the output log file:

```
$ tail -F tmp/log/cooker/<machine>/console-latest.log | grep "Pressure status_
↪changed"
NOTE: Pressure status changed to CPU: False, IO: None, Mem: None (CPU: 1105.9/
↪2.0, IO: 0.0/2.0, Mem: 0.0/2.0) - using 1/64 bitbake threads
...
```

Take a look at the value between parenthesis: CPU: 1105.9/2.0, IO: 0.0/2.0, Mem: 0.0/2.0. They correspond to the current pressure value for the CPU, IO and memory respectively. If *BitBake* prints these messages a lot, it is likely that your pressure limit is too low, and thus can be raised to a higher value.

- ***BB\_LOADFACTOR\_MAX***:

This variable will limit the number of threads *BitBake* will start by monitoring the current CPU load of the host system. *BitBake* will print the following when the limit set by *BB\_LOADFACTOR\_MAX* is reached:

```
Load average limiting set to True as load average: 0.7188262939453125 - using_
↪37/64 bitbake threads
```

This variable has no effect when any of *BB\_PRESSURE\_MAX\_CPU*, *BB\_PRESSURE\_MAX\_IO* or *BB\_PRESSURE\_MAX\_MEMORY* is set, as it was designed for systems that do not have pressure information available.

## 8.18 Working With Libraries

Libraries are an integral part of your system. This section describes some common practices you might find helpful when working with libraries to build your system:

- *How to include static library files*
- *How to use the Multilib feature to combine multiple versions of library files into a single image*
- *How to install multiple versions of the same library in parallel on the same system*

### 8.18.1 Including Static Library Files

If you are building a library and the library offers static linking, you can control which static library files (\*.a files) get included in the built library.

The `PACKAGES` and `FILES:*` variables in the `meta/conf/bitbake.conf` configuration file define how files installed by the `do_install` task are packaged. By default, the `PACKAGES` variable includes `${PN}-staticdev`, which represents all static library files.

#### Nota

Some previously released versions of the Yocto Project defined the static library files through `${PN}-dev`.

Here is a small part of the BitBake configuration file, where you can see how the static library files are defined:

```
PACKAGES = "${PN}-src ${PN}-dbg ${PN}-staticdev ${PN}-dev ${PN}-doc ${PN}-locale $
↪{PACKAGE_BEFORE_PN} ${PN}"

FILES:${PN}-staticdev = "${libdir}/*.a ${base_libdir}/*.a ${libdir}/${BPN}/*.a"
SECTION:${PN}-staticdev = "devel"
RDEPENDS:${PN}-staticdev = "${PN}-dev (= ${EXTENDPKGVS})"
```

### 8.18.2 Combining Multiple Versions of Library Files into One Image

The build system offers the ability to build libraries with different target optimizations or architecture formats and combine these together into one system image. You can link different binaries in the image against the different libraries as needed for specific use cases. This feature is called "Multilib".

An example would be where you have most of a system compiled in 32-bit mode using 32-bit libraries, but you have something large, like a database engine, that needs to be a 64-bit application and uses 64-bit libraries. Multilib allows you to get the best of both 32-bit and 64-bit libraries.

While the Multilib feature is most commonly used for 32 and 64-bit differences, the approach the build system uses facilitates different target optimizations. You could compile some binaries to use one set of libraries and other binaries to use a different set of libraries. The libraries could differ in architecture, compiler options, or other optimizations.

There are several examples in the `meta-skeleton` layer found in *OpenEmbedded-Core (OE-Core)*:

- `conf/multilib-example.conf` configuration file.

- `conf/multilib-example2.conf` configuration file.
- `recipes-multilib/images/core-image-multilib-example.bb` recipe

## Preparing to Use Multilib

User-specific requirements drive the Multilib feature. Consequently, there is no one "out-of-the-box" configuration that would meet your needs.

In order to enable Multilib, you first need to ensure your recipe is extended to support multiple libraries. Many standard recipes are already extended and support multiple libraries. You can check in the `meta/conf/multilib.conf` configuration file in *OpenEmbedded-Core (OE-Core)* to see how this is done using the `BBCLASSEXTEND` variable. Eventually, all recipes will be covered and this list will not be needed.

For the most part, the *Multilib* class extension works automatically to extend the package name from `${PN}` to `${MLPREFIX}${PN}`, where *MLPREFIX* is the particular multilib (e.g. "lib32-" or "lib64-"). Standard variables such as *DEPENDS*, *RDEPENDS*, *RPROVIDES*, *RRECOMMENDS*, *PACKAGES*, and *PACKAGES\_DYNAMIC* are automatically extended by the system. If you are extending any manual code in the recipe, you can use the `${MLPREFIX}` variable to ensure those names are extended correctly.

## Using Multilib

After you have set up the recipes, you need to define the actual combination of multiple libraries you want to build. You can accomplish this through your `build/conf/local.conf` configuration file in the *Build Directory*, or a custom machine *configuration file*. An example configuration would be as follows:

```
MACHINE = "qemux86-64"
require conf/multilib.conf
MULTILIBS = "multilib:lib32"
DEFAULTTUNE:virtclass-multilib-lib32 = "x86"
IMAGE_INSTALL:append = " lib32-glib-2.0"
```

This example enables an additional library named `lib32` alongside the normal target packages. When combining these "lib32" alternatives, the example uses "x86" for tuning. For information on this particular tuning, see `meta/conf/machine/include/ia32/arch-ia32.inc`.

The example then includes `lib32-glib-2.0` in all the images, which illustrates one method of including a multiple library dependency. You can use a normal image build to include this dependency, for example:

```
$ bitbake core-image-sato
```

You can also build Multilib packages specifically with a command like this:

```
$ bitbake lib32-glib-2.0
```

## Additional Implementation Details

There are generic implementation details as well as details that are specific to package management systems. Here are implementation details that exist regardless of the package management system:

- The typical convention used for the class extension code as used by Multilib assumes that all package names specified in *PACKAGES* that contain `${PN}` have `${PN}` at the start of the name. When that convention is not followed and `${PN}` appears at the middle or the end of a name, problems occur.
- The *TARGET\_VENDOR* value under Multilib will be extended to "-vendormlibmultilib" (e.g. "-pokymllib32" for a "lib32" Multilib with Poky). The reason for this slightly unwieldy contraction is that any "-" characters in the vendor string presently break Autoconf's `config.sub`, and other separators are problematic for different reasons.

Here are the implementation details for the RPM Package Management System:

- A unique architecture is defined for the Multilib packages, along with creating a unique deploy folder under `tmp/deploy/rpm` in the *Build Directory*. For example, consider `lib32` in a `qemux86-64` image. The possible architectures in the system are "all", "qemux86\_64", "lib32:qemux86\_64", and "lib32:x86".
- The `${MLPREFIX}` variable is stripped from `${PN}` during RPM packaging. The naming for a normal RPM package and a Multilib RPM package in a `qemux86-64` system resolves to something similar to `bash-4.1-r2.x86_64.rpm` and `bash-4.1-r2.lib32_x86.rpm`, respectively.
- When installing a Multilib image, the RPM backend first installs the base image and then installs the Multilib libraries.
- The build system relies on RPM to resolve the identical files in the two (or more) Multilib packages.

Here are the implementation details for the IPK Package Management System:

- The `${MLPREFIX}` is not stripped from `${PN}` during IPK packaging. The naming for a normal RPM package and a Multilib IPK package in a `qemux86-64` system resolves to something like `bash_4.1-r2.x86_64.ipk` and `lib32-bash_4.1-rw:x86.ipk`, respectively.
- The IPK deploy folder is not modified with `${MLPREFIX}` because packages with and without the Multilib feature can exist in the same folder due to the `${PN}` differences.
- IPK defines a sanity check for Multilib installation using certain rules for file comparison, overridden, etc.

### 8.18.3 Installing Multiple Versions of the Same Library

There might be situations where you need to install and use multiple versions of the same library on the same system at the same time. This almost always happens when a library API changes and you have multiple pieces of software that depend on the separate versions of the library. To accommodate these situations, you can install multiple versions of the same library in parallel on the same system.

The process is straightforward as long as the libraries use proper versioning. With properly versioned libraries, all you need to do to individually specify the libraries is create separate, appropriately named recipes where the *PN* part of the name includes a portion that differentiates each library version (e.g. the major part of the version number). Thus, instead of having a single recipe that loads one version of a library (e.g. `clutter`), you provide multiple recipes that result in different versions of the libraries you want. As an example, the following two recipes would allow the two separate versions of the `clutter` library to co-exist on the same system:

```
clutter-1.6_1.6.20.bb
clutter-1.8_1.8.4.bb
```

Additionally, if you have other recipes that depend on a given library, you need to use the `DEPENDS` variable to create the dependency. Continuing with the same example, if you want to have a recipe depend on the 1.8 version of the `clutter` library, use the following in your recipe:

```
DEPENDS = "clutter-1.8"
```

## 8.19 Working with Pre-Built Libraries

### 8.19.1 Introduzione

Some library vendors do not release source code for their software but do release pre-built binaries. When shared libraries are built, they should be versioned (see [this article](#) for some background), but sometimes this is not done.

To summarize, a versioned library must meet two conditions:

1. The filename must have the version appended, for example: `libfoo.so.1.2.3`.
2. The library must have the ELF tag `SONAME` set to the major version of the library, for example: `libfoo.so.1`.  
You can check this by running `readelf -d filename | grep SONAME`.

This section shows how to deal with both versioned and unversioned pre-built libraries.

### 8.19.2 Versioned Libraries

In this example we work with pre-built libraries for the FT4222H USB I/O chip. Libraries are built for several target architecture variants and packaged in an archive as follows:

```
|— build-arm-hisiv300
|   └─ libft4222.so.1.4.4.44
|— build-arm-v5-sf
|   └─ libft4222.so.1.4.4.44
|— build-arm-v6-hf
|   └─ libft4222.so.1.4.4.44
|— build-arm-v7-hf
|   └─ libft4222.so.1.4.4.44
|— build-arm-v8
|   └─ libft4222.so.1.4.4.44
|— build-i386
|   └─ libft4222.so.1.4.4.44
|— build-i486
|   └─ libft4222.so.1.4.4.44
|— build-mips-eglibc-hf
|   └─ libft4222.so.1.4.4.44
|— build-pentium
```

(continues on next page)



(continua dalla pagina precedente)

```

|   └─ libft4222.so.1.4.4.44
├─ build-x86_64
|   └─ libft4222.so.1.4.4.44
├─ examples
|   └─ get-version.c
|   └─ i2cm.c
|   └─ spim.c
|   └─ spis.c
├─ ftd2xx.h
├─ install4222.sh
├─ libft4222.h
├─ ReadMe.txt
└─ WinTypes.h

```

To write a recipe to use such a library in your system:

- The vendor will probably have a proprietary licence, so set `LICENSE_FLAGS` in your recipe.
- The vendor provides a tarball containing libraries so set `SRC_URI` appropriately.
- Set `COMPATIBLE_HOST` so that the recipe cannot be used with an unsupported architecture. In the following example, we only support the 32 and 64 bit variants of the x86 architecture.
- As the vendor provides versioned libraries, we can use `oe_soinstall` from *utils* to install the shared library and create symbolic links. If the vendor does not do this, we need to follow the non-versioned library guidelines in the next section.
- As the vendor likely used `LDFLAGS` different from those in your Yocto Project build, disable the corresponding checks by adding `ldflags` to `INSANE_SKIP`.
- The vendor will typically ship release builds without debugging symbols. Avoid errors by preventing the packaging task from stripping out the symbols and adding them to a separate debug package. This is done by setting the `INHIBIT_` flags shown below.

The complete recipe would look like this:

```

SUMMARY = "FTDI FT4222H Library"
SECTION = "libs"
LICENSE_FLAGS = "ftdi"
LICENSE = "CLOSED"

COMPATIBLE_HOST = "(i.86|x86_64).*-linux"

# Sources available in a .tgz file in .zip archive
# at https://ftdichip.com/wp-content/uploads/2021/01/libft4222-linux-1.4.4.44.zip
# Found on https://ftdichip.com/software-examples/ft4222h-software-examples/
# Since dealing with this particular type of archive is out of topic here,
# we use a local link.

```

(continues on next page)

(continua dalla pagina precedente)

```

SRC_URI = "file://libft4222-linux-${PV}.tgz"

S = "${UNPACKDIR}"

ARCH_DIR:x86-64 = "build-x86_64"
ARCH_DIR:i586 = "build-i386"
ARCH_DIR:i686 = "build-i386"

INSANE_SKIP:${PN} = "ldflags"
INHIBIT_PACKAGE_STRIP = "1"
INHIBIT_SYSROOT_STRIP = "1"
INHIBIT_PACKAGE_DEBUG_SPLIT = "1"

do_install () {
    install -m 0755 -d ${D}${libdir}
    oe_soinstall ${S}/${ARCH_DIR}/libft4222.so.${PV} ${D}${libdir}
    install -d ${D}${includedir}
    install -m 0755 ${S}/*.h ${D}${includedir}
}

```

If the precompiled binaries are not statically linked and have dependencies on other libraries, then by adding those libraries to *DEPENDS*, the linking can be examined and the appropriate *RDEPENDS* automatically added.

## 8.19.3 Non-Versioned Libraries

### Some Background

Libraries in Linux systems are generally versioned so that it is possible to have multiple versions of the same library installed, which eases upgrades and support for older software. For example, suppose that in a versioned library, an actual library is called `libfoo.so.1.2`, a symbolic link named `libfoo.so.1` points to `libfoo.so.1.2`, and a symbolic link named `libfoo.so` points to `libfoo.so.1.2`. Given these conditions, when you link a binary against a library, you typically provide the unversioned file name (i.e. `-lfoo` to the linker). However, the linker follows the symbolic link and actually links against the versioned filename. The unversioned symbolic link is only used at development time. Consequently, the library is packaged along with the headers in the development package `${PN}-dev` along with the actual library and versioned symbolic links in `${PN}`. Because versioned libraries are far more common than unversioned libraries, the default packaging rules assume versioned libraries.

### Yocto Library Packaging Overview

It follows that packaging an unversioned library requires a bit of work in the recipe. By default, `libfoo.so` gets packaged into `${PN}-dev`, which triggers a QA warning that a non-symlink library is in a `-dev` package, and binaries in the same recipe link to the library in `${PN}-dev`, which triggers more QA warnings. To solve this problem, you need to package the unversioned library into `${PN}` where it belongs. The abridged default *FILES* variables in `bitbake.conf` are:

```

SOLIBS = ".so.*"
SOLIBSDEV = ".so"
FILES:${PN} = "... ${libdir}/lib*${SOLIBS} ... ${base_libdir}/*${SOLIBS} ..."
FILES_SOLIBSDEV ?= "${base_libdir}/lib*${SOLIBSDEV} ${libdir}/lib*${SOLIBSDEV}"
FILES:${PN}-dev = "... ${FILES_SOLIBSDEV} ..."

```

*SOLIBS* defines a pattern that matches real shared object libraries. *SOLIBSDEV* matches the development form (unversioned symlink). These two variables are then used in `FILES:${PN}` and `FILES:${PN}-dev`, which puts the real libraries into `${PN}` and the unversioned symbolic link into `${PN}-dev`. To package unversioned libraries, you need to modify the variables in the recipe as follows:

```

SOLIBS = ".so"
FILES_SOLIBSDEV = ""

```

The modifications cause the `.so` file to be the real library and unset *FILES\_SOLIBSDEV* so that no libraries get packaged into `${PN}-dev`. The changes are required because unless *PACKAGES* is changed, `${PN}-dev` collects files before `${PN}`. `${PN}-dev` must not collect any of the files you want in `${PN}`.

Finally, loadable modules, essentially unversioned libraries that are linked at runtime using `dlopen()` instead of at build time, should generally be installed in a private directory. However, if they are installed in `${libdir}`, then the modules can be treated as unversioned libraries.

## Example

The example below installs an unversioned x86-64 pre-built library named `libfoo.so`. The *COMPATIBLE\_HOST* variable limits recipes to the x86-64 architecture while the *INSANE\_SKIP*, *INHIBIT\_PACKAGE\_STRIP* and *INHIBIT\_SYSROOT\_STRIP* variables are all set as in the above versioned library example. The "magic" is setting the *SOLIBS* and *FILES\_SOLIBSDEV* variables as explained above:

```

SUMMARY = "libfoo sample recipe"
SECTION = "libs"
LICENSE = "CLOSED"

SRC_URI = "file://libfoo.so"

COMPATIBLE_HOST = "x86_64.*-linux"

INSANE_SKIP:${PN} = "ldflags"
INHIBIT_PACKAGE_STRIP = "1"
INHIBIT_SYSROOT_STRIP = "1"
SOLIBS = ".so"
FILES_SOLIBSDEV = ""

do_install () {
    install -d ${D}${libdir}

```

(continues on next page)

(continua dalla pagina precedente)

```
install -m 0755 ${UNPACKDIR}/libfoo.so ${D}${libdir}
}
```


## 8.20 Using the `devtool` command-line tool

The `devtool` command-line tool provides a number of features that help you build, test, and package software. This command is available alongside the `bitbake` command. Additionally, the `devtool` command is a key part of the *Extensible Software Development Kit (eSDK)*.

### 8.20.1 Use `devtool add` to Add an Application

The `devtool add` command generates a new recipe based on existing source code. This command takes advantage of the *The Workspace Layer Structure* layer that many `devtool` commands use. The command is flexible enough to allow you to extract source code into both the workspace or a separate local Git repository and to use existing code that does not need to be extracted.

Depending on your particular scenario, the arguments and options you use with `devtool add` form different combinations. The following diagram shows common development flows you would use with the `devtool add` command:



1. *Generating the New Recipe:* The top part of the flow shows three scenarios by which you could use `devtool` add to generate a recipe based on existing source code.

In a shared development environment, it is typical for other developers to be responsible for various areas of source code. As a developer, you are probably interested in using that source code as part of your development within the Yocto Project. All you need is access to the code, a recipe, and a controlled area in which to do your work.

Within the diagram, three possible scenarios feed into the `devtool add` workflow:

- *Left:* The left scenario in the figure represents a common situation where the source code does not exist locally and needs to be extracted. In this situation, the source code is extracted to the default workspace --- you do not want the files in some specific location outside of the workspace. Thus, everything you need will be located in the workspace:

```
$ devtool add recipe fetchuri
```

With this command, `devtool` extracts the upstream source files into a local Git repository within the `sources` folder. The command then creates a recipe named `recipe` and a corresponding append file in the workspace. If you do not provide `recipe`, the command makes an attempt to determine the recipe name.

- *Middle:* The middle scenario in the figure also represents a situation where the source code does not exist locally. In this case, the code is again upstream and needs to be extracted to some local area --- this time outside of the default workspace.

**i Nota**

If required, `devtool` always creates a Git repository locally during the extraction.

Furthermore, the first positional argument `srcree` in this case identifies where the `devtool add` command will locate the extracted code outside of the workspace. You need to specify an empty directory:

```
$ devtool add recipe srcree fetchuri
```

In summary, the source code is pulled from `fetchuri` and extracted into the location defined by `srcree` as a local Git repository.

Within workspace, `devtool` creates a recipe named `recipe` along with an associated append file.

- *Right:* The right scenario in the figure represents a situation where the `srcree` has been previously prepared outside of the `devtool` workspace.

The following command provides a new recipe name and identifies the existing source tree location:

```
$ devtool add recipe srcree
```

The command examines the source code and creates a recipe named `recipe` for the code and places the recipe into the workspace.

Because the extracted source code already exists, `devtool` does not try to relocate the source code into the workspace --- only the new recipe is placed in the workspace.

Aside from a recipe folder, the command also creates an associated append folder and places an initial `*.bbappend` file within.

2. *Edit the Recipe:* You can use `devtool edit-recipe` to open up the editor as defined by the `$EDITOR` environment variable and modify the file:

```
$ devtool edit-recipe recipe
```

From within the editor, you can make modifications to the recipe that take effect when you build it later.

3. *Build the Recipe or Rebuild the Image:* The next step you take depends on what you are going to do with the new code.

If you need to eventually move the build output to the target hardware, use the following `devtool` command:

```
$ devtool build recipe
```

On the other hand, if you want an image to contain the recipe's packages from the workspace for immediate deployment onto a device (e.g. for testing purposes), you can use the `devtool build-image` command:

```
$ devtool build-image image
```

4. *Deploy the Build Output:* When you use the `devtool build` command to build out your recipe, you probably want to see if the resulting build output works as expected on the target hardware.

#### Nota

This step assumes you have a previously built image that is already either running in QEMU or is running on actual hardware. Also, it is assumed that for deployment of the image to the target, SSH is installed in the image and, if the image is running on real hardware, you have network access to and from your development machine.

You can deploy your build output to that target hardware by using the `devtool deploy-target` command:

```
$ devtool deploy-target recipe target
```

The target is a live target machine running as an SSH server.

You can, of course, also deploy the image you build to actual hardware by using the `devtool build-image` command. However, `devtool` does not provide a specific command that allows you to deploy the image to actual hardware.

5. *Finish Your Work With the Recipe:* The `devtool finish` command creates any patches corresponding to commits in the local Git repository, moves the new recipe to a more permanent layer, and then resets the recipe so that the recipe is built normally rather than from the workspace:

```
$ devtool finish recipe layer
```

#### Nota

Any changes you want to turn into patches must be committed to the Git repository in the source tree.

As mentioned, the `devtool finish` command moves the final recipe to its permanent layer.

As a final process of the `devtool finish` command, the state of the standard layers and the upstream source is restored so that you can build the recipe from those areas rather than the workspace.

**Nota**


You can use the `devtool reset` command to put things back should you decide you do not want to proceed with your work. If you do use this command, realize that the source tree is preserved.

## 8.20.2 Use `devtool modify` to Modify the Source of an Existing Component

The `devtool modify` command prepares the way to work on existing code that already has a local recipe in place that is used to build the software. The command is flexible enough to allow you to extract code from an upstream source, specify the existing recipe, and keep track of and gather any patch files from other developers that are associated with the code.

Depending on your particular scenario, the arguments and options you use with `devtool modify` form different combinations. The following diagram shows common development flows for the `devtool modify` command:





1. *Preparing to Modify the Code:* The top part of the flow shows three scenarios by which you could use `devtool` `modify` to prepare to work on source files. Each scenario assumes the following:

- The recipe exists locally in a layer external to the `devtool` workspace.
- The source files exist either upstream in an un-extracted state or locally in a previously extracted state.

The typical situation is where another developer has created a layer for use with the Yocto Project and their

recipe already resides in that layer. Furthermore, their source code is readily available either upstream or locally.

- *Left*: The left scenario in the figure represents a common situation where the source code does not exist locally and it needs to be extracted from an upstream source. In this situation, the source is extracted into the default `devtool` workspace location. The recipe, in this scenario, is in its own layer outside the workspace (i.e. `meta-layername`).

The following command identifies the recipe and, by default, extracts the source files:

```
$ devtool modify recipe
```

Once `devtool` locates the recipe, `devtool` uses the recipe's `SRC_URI` statements to locate the source code and any local patch files from other developers.

With this scenario, there is no `sRCTree` argument. Consequently, the default behavior of the `devtool modify` command is to extract the source files pointed to by the `SRC_URI` statements into a local Git structure. Furthermore, the location for the extracted source is the default area within the `devtool` workspace. The result is that the command sets up both the source code and an append file within the workspace while the recipe remains in its original location.

Additionally, if you have any non-patch local files (i.e. files referred to with `file://` entries in `SRC_URI` statement excluding `*.patch/` or `*.diff`), these files are copied to an `oe-local-files` folder under the newly created source tree. Copying the files here gives you a convenient area from which you can modify the files. Any changes or additions you make to those files are incorporated into the build the next time you build the software just as are other changes you might have made to the source.

- *Middle*: The middle scenario in the figure represents a situation where the source code also does not exist locally. In this case, the code is again upstream and needs to be extracted to some local area as a Git repository. The recipe, in this scenario, is again local and in its own layer outside the workspace.

The following command tells `devtool` the recipe with which to work and, in this case, identifies a local area for the extracted source files that exists outside of the default `devtool` workspace:

```
$ devtool modify recipe sRCTree
```

#### Nota

You cannot provide a URL for `sRCTree` using the `devtool` command.

As with all extractions, the command uses the recipe's `SRC_URI` statements to locate the source files and any associated patch files. Non-patch files are copied to an `oe-local-files` folder under the newly created source tree.

Once the files are located, the command by default extracts them into `sRCTree`.

Within workspace, `devtool` creates an append file for the recipe. The recipe remains in its original location but the source files are extracted to the location you provide with `sRCTree`.

- *Right:* The right scenario in the figure represents a situation where the source tree (`src tree`) already exists locally as a previously extracted Git structure outside of the `devtool` workspace. In this example, the recipe also exists elsewhere locally in its own layer.

The following command tells `devtool` the recipe with which to work, uses the `-n` option to indicate source does not need to be extracted, and uses `src tree` to point to the previously extracted source files:

```
$ devtool modify -n recipe src tree
```

If an `oe-local-files` subdirectory happens to exist and it contains non-patch files, the files are used. However, if the subdirectory does not exist and you run the `devtool finish` command, any non-patch files that might exist next to the recipe are removed because it appears to `devtool` that you have deleted those files.

Once the `devtool modify` command finishes, it creates only an append file for the recipe in the `devtool` workspace. The recipe and the source code remain in their original locations.

2. *Edit the Source:* Once you have used the `devtool modify` command, you are free to make changes to the source files. You can use any editor you like to make and save your source code modifications.
3. *Build the Recipe or Rebuild the Image:* The next step you take depends on what you are going to do with the new code.

If you need to eventually move the build output to the target hardware, use the following `devtool` command:

```
$ devtool build recipe
```

On the other hand, if you want an image to contain the recipe's packages from the workspace for immediate deployment onto a device (e.g. for testing purposes), you can use the `devtool build-image` command:

```
$ devtool build-image image
```

4. *Deploy the Build Output:* When you use the `devtool build` command to build out your recipe, you probably want to see if the resulting build output works as expected on target hardware.

#### Nota

This step assumes you have a previously built image that is already either running in QEMU or running on actual hardware. Also, it is assumed that for deployment of the image to the target, SSH is installed in the image and if the image is running on real hardware that you have network access to and from your development machine.

You can deploy your build output to that target hardware by using the `devtool deploy-target` command:

```
$ devtool deploy-target recipe target
```

The target is a live target machine running as an SSH server.

You can, of course, use other methods to deploy the image you built using the `devtool build-image` command to actual hardware. `devtool` does not provide a specific command to deploy the image to actual hardware.

5. *Finish Your Work With the Recipe:* The `devtool finish` command creates any patches corresponding to commits in the local Git repository, updates the recipe to point to them (or creates a `.bbappend` file to do so, depending on the specified destination layer), and then resets the recipe so that the recipe is built normally rather than from the workspace:

```
$ devtool finish recipe layer
```

**Nota**

Any changes you want to turn into patches must be staged and committed within the local Git repository before you use the `devtool finish` command.

Because there is no need to move the recipe, `devtool finish` either updates the original recipe in the original layer or the command creates a `.bbappend` file in a different layer as provided by `layer`. Any work you did in the `oe-local-files` directory is preserved in the original files next to the recipe during the `devtool finish` command.

As a final process of the `devtool finish` command, the state of the standard layers and the upstream source is restored so that you can build the recipe from those areas rather than from the workspace.

**Nota**

You can use the `devtool reset` command to put things back should you decide you do not want to proceed with your work. If you do use this command, realize that the source tree is preserved.

### 8.20.3 `devtool ide-sdk` configures IDEs and bootstraps SDKs

The `devtool ide-sdk` command can provide an IDE configuration for IDEs when working on the source code of one or more recipes. Depending on the programming language, and the build system used by the recipe, the tools required for cross-development and remote debugging are different. For example:

- A C/C++ project usually uses CMake or Meson.
- A Python project uses `setuptools` or one of its successors.
- A Rust project uses Cargo.

Also, the IDE plugins needed for the integration of a build system with the IDE and the corresponding settings are usually specific to these build-systems. To hide all these details from the user, `devtool ide-sdk` does two things:

- It generates any kind of SDK needed for cross-development and remote debugging of the specified recipes.
- It generates the configuration for the IDE (and the IDE plugins) for using the cross-toolchain and remote debugging tools provided by the SDK directly from the IDE.

For supported build systems the configurations generated by `devtool ide-sdk` combine the advantages of the `devtool modify` based workflow (see [Using devtool in Your SDK Workflow](#)) with the advantages of the simple Environment Setup script based workflow (see [Running the Extensible SDK Environment Setup Script](#)) provided by Yocto's SDK or eSDK:

- The source code of the recipe is in the workspace created by `devtool modify` or `devtool add`. Using `devtool build`, `devtool build-image`, `devtool deploy-target` or `bitbake` is possible. Also `devtool ide-sdk` can be used to update the SDK and the IDE configuration at any time.
- `devtool ide-sdk` aims to support multiple programming languages and multiple IDEs natively. "Natively" means that the IDE is configured to call the build tool (e.g. `cmake` or `meson`) directly. This has several advantages. First of all, it is usually much faster to call for example `cmake` than `devtool build`. It also allows to benefit from the very good integration that IDEs like VSCode offer for tools like CMake or GDB.

However, supporting many programming languages and multiple IDEs is quite an elaborate and constantly evolving thing. Support for IDEs is therefore implemented as plugins. Plugins can also be provided by optional layers.

So much about the introduction to the default mode of `devtool sdk-ide` which is called the "modified" mode because it uses the workspace created by `devtool modify` and the per recipe *Sysroots* of BitBake.

For some recipes and use cases, this default behavior of `devtool ide-sdk` with full `devtool` and `bitbake` integration might not be suitable. To offer full feature parity with the SDK and the eSDK, `devtool ide-sdk` has a second mode called "shared" mode. If `devtool ide-sdk` is called with the `--mode=shared` option, it bootstraps an SDK directly from the BitBake environment, which offers the same Environment Setup script as described in [Running the Extensible SDK Environment Setup Script](#). In addition to the (e)SDK installer-based setup, the IDE gets configured to use the shared *Sysroots* and the tools from the SDK. `devtool ide-sdk --mode=shared` is basically a wrapper for the setup of the extensible SDK as described in [Setting up the Extensible SDK environment directly in a Yocto build](#).

The use of `devtool ide-sdk` is an alternative to using one of the SDK installers. `devtool ide-sdk` allows the creation of SDKs that offer all the functionality of the SDK and the eSDK installers. Compared to the installers, however, the SDK created with `devtool ide-sdk` is much more flexible. For example, it is very easy to change the *MACHINE* in the `build/conf/local.conf` file, update the layer meta data and then regenerate the SDK.

Let's take a look at an example of how to use `devtool ide-sdk` in each of the two modes:

#### 1. Modified mode:

In order to use the `devtool ide-sdk`, a few settings are needed. As a starting example, the following lines of code can be added to the `build/conf/local.conf` file:

```
# Build the companion debug file system
IMAGE_GEN_DEBUGFS = "1"

# Optimize build time: with devtool ide-sdk the dbg tar is not needed
IMAGE_FSTYPES_DEBUGFS = ""

# Without copying the binaries into roofs-dbg, GDB does not find all source
↪files.
IMAGE_CLASSES += "image-combined-dbg"
```

(continues on next page)

(continua dalla pagina precedente)

```
# SSH is mandatory, no password simplifies the usage
EXTRA_IMAGE_FEATURES += "\
    ssh-server-openssh \
    allow-empty-password \
    allow-root-login \
    empty-root-password \
"

# Remote debugging needs gdbserver on the target device
IMAGE_INSTALL:append = " gdbserver"

# Add the recipes which should be modified to the image
# Otherwise some dependencies might be missing.
IMAGE_INSTALL:append = " my-recipe"
```

Assuming the BitBake environment is set up correctly and a workspace has been created for the recipe using `devtool modify my-recipe` or probably even better by using `devtool modify my-recipe --debug-build`, the following command can create the SDK and the configuration for VSCode in the recipe workspace:

```
$ devtool ide-sdk my-recipe core-image-minimal --target root@192.168.7.2
```

The command requires an image recipe (`core-image-minimal` for this example) that is used to create the SDK. This firmware image should also be installed on the target device. It is possible to pass multiple package recipes:

```
$ devtool ide-sdk my-recipe-1 my-recipe-2 core-image-minimal --target root@192.
→168.7.2
```

`devtool ide-sdk` tries to create an IDE configuration for all package recipes.

What this command does exactly depends on the recipe, more precisely on the build tool used by the recipe. The basic idea is to configure the IDE so that it calls the build tool exactly as `bitbake` does.

For example, a CMake preset is created for a recipe that inherits `cmake`. In the case of VSCode, CMake presets are supported by the CMake Tools plugin. This is an example of how the build configuration used by `bitbake` is exported to an IDE configuration that gives exactly the same build results.

Support for remote debugging with seamless integration into the IDE is important for a cross-SDK. `devtool ide-sdk` automatically generates the necessary helper scripts for deploying the compiled artifacts to the target device as well as the necessary configuration for the debugger and the IDE.

#### Nota

To ensure that the debug symbols on the build machine match the binaries running on the target device, it is essential that the image built by `devtool ide-sdk` is running on the target device.

The default IDE is VSCode. Some hints about using VSCode:

- VSCode can be used to work on the BitBake recipes or the application source code. Usually there is one instance of VSCode running in the folder where the BitBake recipes are. This instance has the [Yocto Project BitBake plugin](#) running.

#### Avvertimento

Some VSCode plugins (Python, BitBake and others) need a reasonable configuration to work as expected. Otherwise, some plugins try to index the build directory of BitBake, which keeps your system quite busy until an out of memory exception stops this nonsense. Other plugins, such as the BitBake plugin, do not behave as expected.

To work around such issues, the `oe-init-build-env` script creates an initial `.vscode/settings.json` file if code can be found and the `.vscode` folder does not yet exist. It is best to run `oe-init-build-env` once before starting VSCode. An alternative approach is to use a build folder outside the layers, e.g. `oe-init-build-env ../build`.

The BitBake plugin also offers to create devtool workspaces and run `devtool ide-sdk` with a few mouse clicks. Of course, issuing commands in the terminal works as well.

- To work on the source code of a recipe another instance of VSCode is started in the recipe's workspace. Example:

```
code build/workspace/sources/my-recipe
```

This instance of VSCode uses plugins that are useful for the development of the application. `devtool ide-sdk` generates the necessary `extensions.json`, `settings.json`, `tasks.json` and `launch.json` configuration files for all the involved plugins.

When the source code folder present in the workspace folder is opened in VSCode for the first time, a pop-up message recommends installing the required plugins. After accepting the installation of the plugins, working with the source code or some debugging tasks should work as usual with VSCode.

Starting the VSCode instances in the recipe workspace folders can also be done by a mouse click on the recipe workspaces in the first VSCode instance.

- To work with CMake press `Ctrl + Shift + p`, type `cmake`. This will show some possible commands like selecting a CMake preset, compiling or running CTest.

For recipes inheriting `cmake-qemu` rather than `cmake`, executing cross-compiled unit tests on the host can be supported transparently with QEMU user-mode.

- To work with Meson press `Ctrl + Shift + p`, type `meson`. This will show some possible commands like compiling or executing the unit tests.

A note on running cross-compiled unit tests on the host: Meson enables support for QEMU user mode by default. It is expected that the execution of the unit tests from the IDE will work without any additional steps, given that the code is suitable for the execution on the host machine.

- For the deployment to the target device, just press `Ctrl + Shift + p`, type `task`. Select `install && deploy-target`.
- For remote debugging, switch to the debugging view by pressing the "play" button with the `bug` icon on the left side. This will provide a green play button with a drop-down list where a debug configuration can be selected. After selecting one of the generated configurations, press the "play" button.

Starting a remote debugging session automatically initiates the deployment to the target device. If this is not desired, the `"dependsOn": ["install && deploy-target..."]` parameter of the tasks with `"label": "gdbserver start..."` can be removed from the `tasks.json` file.

VSCode supports GDB with many different setups and configurations for many different use cases. However, most of these setups have some limitations when it comes to cross-development, support only a few target architectures or require a high performance target device. Therefore `devtool ide-sdk` supports the classic, generic setup with GDB on the development host and `gdbserver` on the target device.

Roughly summarized, this means:

- The binaries are copied via SSH to the remote target device by a script referred by `tasks.json`.
- `gdbserver` is started on the remote target device via SSH by a script referred by `tasks.json`.

Changing the parameters that are passed to the debugging executable requires modifying the generated script. The script is located at `oe-scripts/gdbserver_*`. Defining the parameters in the `args` field in the `launch.json` file does not work.

- VSCode connects to `gdbserver` as documented in [Remote debugging or debugging with a local debugger server](#).

Additionally `--ide=none` is supported. With the `none` IDE parameter, some generic configuration files like `gdbinit` files and some helper scripts starting `gdbserver` remotely on the target device as well as the GDB client on the host are generated.

Here is a usage example for the `cmake-example` recipe from the `meta-selftest` layer which inherits `cmake-qemu`:

```
# Create the SDK
devtool modify cmake-example --debug-build
devtool ide-sdk cmake-example core-image-minimal -c --ide=none

# Install the firmware on a target device or start QEMU
runqemu

# From exploring the workspace of cmake-example
cd build/workspace/sources/cmake-example

# Find cmake-native and save the path into a variable
# Note: using just cmake instead of $CMAKE_NATIVE would work in many cases
CMAKE_NATIVE="$(jq -r '.configurePresets[0] | \"\(.cmakeExecutable)\"' \
↳ CMakeUserPresets.json) "
```

(continues on next page)



(continua dalla pagina precedente)

```

# List available CMake presets
"$CMAKE_NATIVE" --list-presets
Available configure presets:

  "cmake-example-cortexa57" - cmake-example: cortexa57

# Re-compile the already compiled sources
"$CMAKE_NATIVE" --build --preset cmake-example-cortexa57
ninja: no work to do.
# Do a clean re-build
"$CMAKE_NATIVE" --build --preset cmake-example-cortexa57 --target clean
[1/1] Cleaning all built files...
Cleaning... 8 files.
"$CMAKE_NATIVE" --build --preset cmake-example-cortexa57 --target all
[7/7] Linking CXX executable cmake-example

# Run the cross-compiled unit tests with QEMU user-mode
"$CMAKE_NATIVE" --build --preset cmake-example-cortexa57 --target test
[0/1] Running tests...
Test project .../build/tmp/work/cortexa57-poky-linux/cmake-example/1.0/cmake-
→example-1.0
   Start 1: test-cmake-example
1/1 Test #1: test-cmake-example ..... Passed    0.03 sec

100% tests passed, 0 tests failed out of 1

Total Test time (real) =    0.03 sec

# Using CTest directly is possible as well
CTEST_NATIVE="$ (dirname "$CMAKE_NATIVE")/ctest"

# List available CMake presets
"$CTEST_NATIVE" --list-presets
Available test presets:

  "cmake-example-cortexa57" - cmake-example: cortexa57

# Run the cross-compiled unit tests with QEMU user-mode
"$CTEST_NATIVE" --preset "cmake-example-cortexa57"
Test project ...build/tmp/work/cortexa57-poky-linux/cmake-example/1.0/cmake-
→example-1.0
   Start 1: test-cmake-example
1/1 Test #1: test-cmake-example ..... Passed    0.03 sec

```

(continues on next page)

(continua dalla pagina precedente)

```

100% tests passed, 0 tests failed out of 1

Total Test time (real) = 0.03 sec

# Deploying the new build to the target device (default is QEUM at 192.168.7.2)
oe-scripts/install_and_deploy_cmake-example-cortexa57

# Start a remote debugging session with gdbserver on the target and GDB on the
↪host
oe-scripts/gdbserver_1234_usr-bin-cmake-example_m
oe-scripts/gdb_1234_usr-bin-cmake-example
break main
run
step
stepi
continue
quit

# Stop gdbserver on the target device
oe-scripts/gdbserver_1234_usr-bin-cmake-example_m stop

```

## 2. Shared sysroots mode

Creating an SDK with shared *Sysroots* that contains all the dependencies needed to work with `my-recipe` is possible with the following example command:

```
$ devtool ide-sdk --mode=shared my-recipe
```

For VSCode the cross-toolchain is exposed as a CMake kit. CMake kits are defined in `~/.local/share/CMakeTools/cmake-tools-kits.json`. The following example shows how the cross-toolchain can be selected in VSCode. First of all we need a folder containing a CMake project. For this example, let's create a CMake project and start VSCode:

```

mkdir kit-test
echo "project(foo VERSION 1.0)" > kit-test/CMakeLists.txt
code kit-test

```

If there is a CMake project in the workspace, cross-compilation is supported:

- Press `Ctrl + Shift + P`, type `CMake: Scan for Kits`
- Press `Ctrl + Shift + P`, type `CMake: Select a Kit`

Finally most of the features provided by CMake and the IDE should be available.

Other IDEs than VSCode are supported as well. However, `devtool ide-sdk --mode=shared --ide=none my-recipe` is currently just a simple wrapper for the setup of the extensible SDK, as described in *Setting up the Extensible SDK environment directly in a Yocto build*.

### 8.20.4 Use `devtool upgrade` to Create a Version of the Recipe that Supports a Newer Version of the Software


The `devtool upgrade` command upgrades an existing recipe to that of a more up-to-date version found upstream. Throughout the life of software, recipes continually undergo version upgrades by their upstream publishers. You can use the `devtool upgrade` workflow to make sure your recipes you are using for builds are up-to-date with their upstream counterparts.

#### Nota

Several methods exist by which you can upgrade recipes --- `devtool upgrade` happens to be one. You can read about all the methods by which you can upgrade recipes in the *Upgrading Recipes* section of the Yocto Project Development Tasks Manual.

The `devtool upgrade` command is flexible enough to allow you to specify source code revision and versioning schemes, extract code into or out of the `devtool` *The Workspace Layer Structure*, and work with any source file forms that the *Fetchers* support.

The following diagram shows the common development flow used with the `devtool upgrade` command:



1. *Initiate the Upgrade:* The top part of the flow shows the typical scenario by which you use the `devtool upgrade` command. The following conditions exist:

- The recipe exists in a local layer external to the `devtool` workspace.
- The source files for the new release exist in the same location pointed to by `SRC_URI` in the recipe (e.g. a tarball with the new version number in the name, or as a different revision in the upstream Git repository).

A common situation is where third-party software has undergone a revision so that it has been upgraded. The recipe you have access to is likely in your own layer. Thus, you need to upgrade the recipe to use the newer version of the software:

```
$ devtool upgrade -V version recipe
```

By default, the `devtool upgrade` command extracts source code into the `sources` directory in the *The Workspace Layer Structure*. If you want the code extracted to any other location, you need to provide the `src tree` positional argument with the command as follows:

```
$ devtool upgrade -V version recipe src tree
```

**i Nota**

In this example, the "-V" option specifies the new version. If you don't use "-V", the command upgrades the recipe to the latest version.

If the source files pointed to by the `SRC_URI` statement in the recipe are in a Git repository, you must provide the "-S" option and specify a revision for the software.

Once `devtool` locates the recipe, it uses the `SRC_URI` variable to locate the source code and any local patch files from other developers. The result is that the command sets up the source code, the new version of the recipe, and an append file all within the workspace.

Additionally, if you have any non-patch local files (i.e. files referred to with `file://` entries in `SRC_URI` statement excluding `*.patch/` or `*.diff`), these files are copied to an `oe-local-files` folder under the newly created source tree. Copying the files here gives you a convenient area from which you can modify the files. Any changes or additions you make to those files are incorporated into the build the next time you build the software just as are other changes you might have made to the source.

2. *Resolve any Conflicts created by the Upgrade:* Conflicts could happen after upgrading the software to a new version. Conflicts occur if your recipe specifies some patch files in `SRC_URI` that conflict with changes made in the new version of the software. For such cases, you need to resolve the conflicts by editing the source and following the normal `git rebase` conflict resolution process.

Before moving onto the next step, be sure to resolve any such conflicts created through use of a newer or different version of the software.

3. *Build the Recipe or Rebuild the Image:* The next step you take depends on what you are going to do with the new code.

If you need to eventually move the build output to the target hardware, use the following `devtool` command:

```
$ devtool build recipe
```

On the other hand, if you want an image to contain the recipe's packages from the workspace for immediate deployment onto a device (e.g. for testing purposes), you can use the `devtool build-image` command:

```
$ devtool build-image image
```

4. *Deploy the Build Output:* When you use the `devtool build` command or `bitbake` to build your recipe, you probably want to see if the resulting build output works as expected on target hardware.

**i Nota**

This step assumes you have a previously built image that is already either running in QEMU or running on actual hardware. Also, it is assumed that for deployment of the image to the target, SSH is installed in the image and if the image is running on real hardware that you have network access to and from your development machine.

You can deploy your build output to that target hardware by using the `devtool deploy-target` command:

```
$ devtool deploy-target recipe target
```

The target is a live target machine running as an SSH server.

You can, of course, also deploy the image you build using the `devtool build-image` command to actual hardware. However, `devtool` does not provide a specific command that allows you to do this.

5. *Finish Your Work With the Recipe:* The `devtool finish` command creates any patches corresponding to commits in the local Git repository, moves the new recipe to a more permanent layer, and then resets the recipe so that the recipe is built normally rather than from the workspace.

Any work you did in the `oe-local-files` directory is preserved in the original files next to the recipe during the `devtool finish` command.

If you specify a destination layer that is the same as the original source, then the old version of the recipe and associated files are removed prior to adding the new version:

```
$ devtool finish recipe layer
```

**i Nota**

Any changes you want to turn into patches must be committed to the Git repository in the source tree.

As a final process of the `devtool finish` command, the state of the standard layers and the upstream source is restored so that you can build the recipe from those areas rather than the workspace.

**i Nota**

You can use the `devtool reset` command to put things back should you decide you do not want to proceed with your work. If you do use this command, realize that the source tree is preserved.

### 8.20.5 A Closer Look at `devtool add`

The `devtool add` command automatically creates a recipe based on the source tree you provide with the command. Currently, the command has support for the following:

- Autotools (`autoconf` and `automake`)
- CMake
- Scons
- `qmake`
- Plain Makefile
- Out-of-tree kernel module
- Binary package (i.e. "-b" option)
- Node.js module
- Python modules that use `setuptools` or `distutils`

Apart from binary packages, the determination of how a source tree should be treated is automatic based on the files present within that source tree. For example, if a `CMakeLists.txt` file is found, then the source tree is assumed to be using CMake and is treated accordingly.

**i Nota**

In most cases, you need to edit the automatically generated recipe in order to make it build properly. Typically, you would go through several edit and build cycles until the recipe successfully builds. Once the recipe builds, you could use possible further iterations to test the recipe on the target device.

The remainder of this section covers specifics regarding how parts of the recipe are generated.

#### Name and Version

If you do not specify a name and version on the command line, `devtool add` uses various metadata within the source tree in an attempt to determine the name and version of the software being built. Based on what the tool determines, `devtool` sets the name of the created recipe file accordingly.

If `devtool` cannot determine the name and version, the command prints an error. For such cases, you must re-run the command and provide the name and version, just the name, or just the version as part of the command line.

Sometimes the name or version determined from the source tree might be incorrect. For such a case, you must reset the recipe:

```
$ devtool reset -n recipename
```

After running the `devtool reset` command, you need to run `devtool add` again and provide the name or the version.

## Dependency Detection and Mapping

The `devtool add` command attempts to detect build-time dependencies and map them to other recipes in the system. During this mapping, the command fills in the names of those recipes as part of the `DEPENDS` variable within the recipe. If a dependency cannot be mapped, `devtool` places a comment in the recipe indicating such. The inability to map a dependency can result from naming not being recognized or because the dependency simply is not available. For cases where the dependency is not available, you must use the `devtool add` command to add an additional recipe that satisfies the dependency. Once you add that recipe, you need to update the `DEPENDS` variable in the original recipe to include the new recipe.

If you need to add runtime dependencies, you can do so by adding the following to your recipe:

```
RDEPENDS:${PN} += "dependency1 dependency2 ..."
```

### Nota

The `devtool add` command often cannot distinguish between mandatory and optional dependencies. Consequently, some of the detected dependencies might in fact be optional. When in doubt, consult the documentation or the configure script for the software the recipe is building for further details. In some cases, you might find you can substitute the dependency with an option that disables the associated functionality passed to the configure script.

## License Detection

The `devtool add` command attempts to determine if the software you are adding is able to be distributed under a common, open-source license. If so, the command sets the `LICENSE` value accordingly. You should double-check the value added by the command against the documentation or source files for the software you are building and, if necessary, update that `LICENSE` value.

The `devtool add` command also sets the `LIC_FILES_CHKSUM` value to point to all files that appear to be license-related. Realize that license statements often appear in comments at the top of source files or within the documentation. In such cases, the command does not recognize those license statements. Consequently, you might need to amend the `LIC_FILES_CHKSUM` variable to point to one or more of those comments if present. Setting `LIC_FILES_CHKSUM` is particularly important for third-party software. The mechanism attempts to ensure correct licensing should you upgrade the recipe to a newer upstream version in future. Any change in licensing is detected and you receive an error prompting you to check the license text again.

If the `devtool add` command cannot determine licensing information, `devtool` sets the `LICENSE` value to "CLOSED" and leaves the `LIC_FILES_CHKSUM` value unset. This behavior allows you to continue with development even though the settings are unlikely to be correct in all cases. You should check the documentation or source files for the software you are building to determine the actual license.



## Adding Makefile-Only Software

The use of Make by itself is very common in both proprietary and open-source software. Unfortunately, Makefiles are often not written with cross-compilation in mind. Thus, `devtool add` often cannot do very much to ensure that these Makefiles build correctly. It is very common, for example, to explicitly call `gcc` instead of using the `CC` variable. Usually, in a cross-compilation environment, `gcc` is the compiler for the build host and the cross-compiler is named something similar to `arm-poky-linux-gnueabi-gcc` and might require arguments (e.g. to point to the associated sysroot for the target machine).

When writing a recipe for Makefile-only software, keep the following in mind:

- You probably need to patch the Makefile to use variables instead of hardcoding tools within the toolchain such as `gcc` and `g++`.
- The environment in which Make runs is set up with various standard variables for compilation (e.g. `CC`, `CXX`, and so forth) in a similar manner to the environment set up by an *SDK*'s environment setup script. One easy way to see these variables is to run the `devtool build` command on the recipe and then look in `oe-logs/run.do_compile`. Towards the top of this file, there is a list of environment variables that are set. You can take advantage of these variables within the Makefile.
- If the Makefile sets a default for a variable using `"="`, that default overrides the value set in the environment, which is usually not desirable. For this case, you can either patch the Makefile so it sets the default using the `"?="` operator, or you can alternatively force the value on the `make` command line. To force the value on the command line, add the variable setting to `EXTRA_OEMAKE` or `PACKAGECONFIG_CONFARGS` within the recipe. Here is an example using `EXTRA_OEMAKE`:

```
EXTRA_OEMAKE += "'CC=${CC}' 'CXX=${CXX}' "
```

In the above example, single quotes are used around the variable settings as the values are likely to contain spaces because required default options are passed to the compiler.

- Hardcoding paths inside Makefiles is often problematic in a cross-compilation environment. This is particularly true because those hardcoded paths often point to locations on the build host and thus will either be read-only or will introduce contamination into the cross-compilation because they are specific to the build host rather than the target. Patching the Makefile to use prefix variables or other path variables is usually the way to handle this situation.
- Sometimes a Makefile runs target-specific commands such as `ldconfig`. For such cases, you might be able to apply patches that remove these commands from the Makefile.

## Adding Native Tools

Often, you need to build additional tools that run on the *Build Host* as opposed to the target. You should indicate this requirement by using one of the following methods when you run `devtool add`:

- Specify the name of the recipe such that it ends with `"-native"`. Specifying the name like this produces a recipe that only builds for the build host.
- Specify the `"--also-native"` option with the `devtool add` command. Specifying this option creates a recipe file that still builds for the target but also creates a variant with a `"-native"` suffix that builds for the build host.

**i Nota**

If you need to add a tool that is shipped as part of a source tree that builds code for the target, you can typically accomplish this by building the native and target parts separately rather than within the same compilation process. Realize though that with the "--also-native" option, you can add the tool using just one recipe file.

## Adding Node.js Modules

**⚠ Avvertimento**

The NPM fetcher is currently disabled due to security concerns. See [355cd22](#) for more information.

You can use the `devtool add` command two different ways to add Node.js modules: through `npm` or from a repository or local source.

Use the following form to add Node.js modules through `npm`:

```
$ devtool add "npm://registry.npmjs.org;name=forever;version=0.15.1"
```

The name and version parameters are mandatory. Lockdown and shrinkwrap files are generated and pointed to by the recipe in order to freeze the version that is fetched for the dependencies according to the first time. This also saves checksums that are verified on future fetches. Together, these behaviors ensure the reproducibility and integrity of the build.

**i Nota**

- You must use quotes around the URL. `devtool add` does not require the quotes, but the shell considers `;"` as a splitter between multiple commands. Thus, without the quotes, `devtool add` does not receive the other parts, which results in several "command not found" errors.

As mentioned earlier, you can also add Node.js modules directly from a repository or local source tree. To add modules this way, use `devtool add` in the following form:

```
$ devtool add https://github.com/diversario/node-ssdp
```

In this example, `devtool` fetches the specified Git repository, detects the code as Node.js code, fetches dependencies using `npm`, and sets `SRC_URI` accordingly.

## 8.20.6 Working With Recipes

When building a recipe using the `devtool build` command, the typical build progresses as follows:

1. Fetch the source
2. Unpack the source
3. Configure the source

4. Compile the source
5. Install the build output
6. Package the installed output

For recipes in the workspace, fetching and unpacking is disabled as the source tree has already been prepared and is persistent. Each of these build steps is defined as a function (task), usually with a "do\_" prefix (e.g. *do\_fetch*, *do\_unpack*, and so forth). These functions are typically shell scripts but can instead be written in Python.

If you look at the contents of a recipe, you will see that the recipe does not include complete instructions for building the software. Instead, common functionality is encapsulated in classes inherited with the `inherit` directive. This technique leaves the recipe to describe just the things that are specific to the software being built. There is a *base* class that is implicitly inherited by all recipes and provides the functionality that most recipes typically need.

The remainder of this section presents information useful when working with recipes.

## Finding Logs and Work Files

After the first run of the `devtool build` command, recipes that were previously created using the `devtool add` command or whose sources were modified using the `devtool modify` command contain symbolic links created within the source tree:

- `oe-logs`: This link points to the directory in which log files and run scripts for each build step are created.
- `oe-workdir`: This link points to the temporary work area for the recipe. The following locations under `oe-workdir` are particularly useful:
  - `image/`: Contains all of the files installed during the *do\_install* stage. Within a recipe, this directory is referred to by the expression `${D}`.
  - `sysroot-destdir/`: Contains a subset of files installed within *do\_install* that have been put into the shared sysroot. For more information, see the "*Sharing Files Between Recipes*" section.
  - `packages-split/`: Contains subdirectories for each package produced by the recipe. For more information, see the "*Packaging*" section.

You can use these links to get more information on what is happening at each build step.

## Setting Configure Arguments

If the software your recipe is building uses GNU autoconf, then a fixed set of arguments is passed to it to enable cross-compilation plus any extras specified by *EXTRA\_OECONF* or *PACKAGECONFIG\_CONFARGS* set within the recipe. If you wish to pass additional options, add them to *EXTRA\_OECONF* or *PACKAGECONFIG\_CONFARGS*. Other supported build tools have similar variables (e.g. *EXTRA\_OECMAKE* for CMake, *EXTRA\_OESCONS* for Scons, and so forth). If you need to pass anything on the `make` command line, you can use *EXTRA\_OEMAKE* or the *PACKAGECONFIG\_CONFARGS* variables to do so.

You can use the `devtool configure-help` command to help you set the arguments listed in the previous paragraph. The command determines the exact options being passed, and shows them to you along with any custom arguments specified through *EXTRA\_OECONF* or *PACKAGECONFIG\_CONFARGS*. If applicable, the command also shows you the output of the configure script's "`--help`" option as a reference.

## Sharing Files Between Recipes

Recipes often need to use files provided by other recipes on the *Build Host*. For example, an application linking to a common library needs access to the library itself and its associated headers. The way this access is accomplished is through the *Sysroot*. There is a sysroot for the target machine, and a sysroot for the build host.

Recipes should never write files directly into the sysroot. Instead, files should be installed into standard locations during the *do\_install* task within the  $\${D}$  directory. A subset of these files automatically goes into the sysroot. The reason for this limitation is that almost all files that go into the sysroot are cataloged in manifests in order to ensure they can be removed later when a recipe is modified or removed. Thus, the sysroot is able to remain free from stale files.

## Packaging

If you examine how build output gets into the final image on the target device, it is important to understand packaging because the contents of the image are expressed in terms of packages and not recipes.

During the *do\_package* task, files installed during the *do\_install* task are split into one main package, which is almost always named the same as the recipe, and into several other packages. This separation exists because not all of those installed files are useful in every image. For example, you probably do not need any of the documentation installed in a production image. Consequently, for each recipe the documentation files are separated into a `-doc` package. Recipes that package software containing optional modules or plugins might undergo additional package splitting as well.

After building a recipe, you can see where files have gone by looking in the `oe-workdir/packages-split` directory, which contains a subdirectory for each package. Apart from some advanced cases, the *PACKAGES* and *FILES* variables controls splitting. The *PACKAGES* variable lists all of the packages to be produced, while the *FILES* variable specifies which files to include in each package by using an override to specify the package. For example, `FILES:${PN}` specifies the files to go into the main package (i.e. the main package has the same name as the recipe and  $\${PN}$  evaluates to the recipe name). The order of the *PACKAGES* value is significant. For each installed file, the first package whose *FILES* value matches the file is the package into which the file goes. Both the *PACKAGES* and *FILES* variables have default values. Consequently, you might find you do not even need to set these variables in your recipe unless the software the recipe is building installs files into non-standard locations.

### 8.20.7 Restoring the Target Device to its Original State

If you use the `devtool deploy-target` command to write a recipe's build output to the target, and you are working on an existing component of the system, then you might find yourself in a situation where you need to restore the original files that existed prior to running the `devtool deploy-target` command. Because the `devtool deploy-target` command backs up any files it overwrites, you can use the `devtool undeploy-target` command to restore those files and remove any other files the recipe deployed. Consider the following example:

```
$ devtool undeploy-target lighttpd root@192.168.7.2
```

If you have deployed multiple applications, you can remove them all using the `-a` option thus restoring the target device to its original state:

```
$ devtool undeploy-target -a root@192.168.7.2
```

Information about files deployed to the target as well as any backed up files are stored on the target itself. This storage, of course, requires some additional space on the target machine.

### **Nota**

The `devtool deploy-target` and `devtool undeploy-target` commands do not currently interact with any package management system on the target device (e.g. RPM or OPKG). Consequently, you should not inter-mingle `devtool deploy-target` and package manager operations on the target device. Doing so could result in a conflicting set of files.

## 8.21 Using x32 psABI

x32 processor-specific Application Binary Interface (**x32 psABI**) is a native 32-bit processor-specific ABI for Intel 64 (x86-64) architectures. An ABI defines the calling conventions between functions in a processing environment. The interface determines what registers are used and what the sizes are for various C data types.

Some processing environments prefer using 32-bit applications even when running on Intel 64-bit platforms. Consider the i386 psABI, which is a very old 32-bit ABI for Intel 64-bit platforms. The i386 psABI does not provide efficient use and access of the Intel 64-bit processor resources, leaving the system underutilized. Now consider the x86\_64 psABI. This ABI is newer and uses 64-bits for data sizes and program pointers. The extra bits increase the footprint size of the programs, libraries, and also increases the memory and file system size requirements. Executing under the x32 psABI enables user programs to utilize CPU and system resources more efficiently while keeping the memory footprint of the applications low. Extra bits are used for registers but not for addressing mechanisms.

The Yocto Project supports the final specifications of x32 psABI as follows:

- You can create packages and images in x32 psABI format on x86\_64 architecture targets.
- You can successfully build recipes with the x32 toolchain.
- You can create and boot `core-image-minimal` and `core-image-sato` images.
- There is RPM Package Manager (RPM) support for x32 binaries.
- There is support for large images.

To use the x32 psABI, you need to edit your `build/conf/local.conf` configuration file as follows:

```
MACHINE = "qemux86-64"
DEFAULTTUNE = "x86-64-x32"
baselib = "${@d.getVar('BASE_LIB:tune-' + (d.getVar('DEFAULTTUNE') \
    or 'INVALID')) or 'lib'}"
```

Once you have set up your configuration file, use BitBake to build an image that supports the x32 psABI. Here is an example:

```
$ bitbake core-image-sato
```

## 8.22 Enabling GObject Introspection Support

**GObject introspection** is the standard mechanism for accessing GObject-based software from runtime environments. GObject is a feature of the GLib library that provides an object framework for the GNOME desktop and related software. GObject Introspection adds information to GObject that allows objects created within it to be represented across different programming languages. If you want to construct GStreamer pipelines using Python, or control UPnP infrastructure using Javascript and GUPnP, GObject introspection is the only way to do it.

This section describes the Yocto Project support for generating and packaging GObject introspection data. GObject introspection data is a description of the API provided by libraries built on top of the GLib framework, and, in particular, that framework's GObject mechanism. GObject Introspection Repository (GIR) files go to `-dev` packages, `typelib` files go to main packages as they are packaged together with libraries that are introspected.

The data is generated when building such a library, by linking the library with a small executable binary that asks the library to describe itself, and then executing the binary and processing its output.

Generating this data in a cross-compilation environment is difficult because the library is produced for the target architecture, but its code needs to be executed on the build host. This problem is solved with the OpenEmbedded build system by running the code through QEMU, which allows precisely that. Unfortunately, QEMU does not always work perfectly as mentioned in the "*Known Issues*" section.

### 8.22.1 Enabling the Generation of Introspection Data

Enabling the generation of introspection data (GIR files) in your library package involves the following:

1. Inherit the `gobject-introspection` class.
2. Make sure introspection is not disabled anywhere in the recipe or from anything the recipe includes. Also, make sure that "gobject-introspection-data" is not in `DISTRO_FEATURES_OPTED_OUT` and that "qemu-usermode" is not in `MACHINE_FEATURES_OPTED_OUT`. In either of these conditions, nothing will happen.
3. Try to build the recipe. If you encounter build errors that look like something is unable to find `.so` libraries, check where these libraries are located in the source tree and add the following to the recipe:

```
GIR_EXTRA_LIBS_PATH = "${B}/something/.libs"
```

#### Nota

See recipes in the `oe-core` repository that use that `GIR_EXTRA_LIBS_PATH` variable as an example.

4. Look for any other errors, which probably mean that introspection support in a package is not entirely standard, and thus breaks down in a cross-compilation environment. For such cases, custom-made fixes are needed. A good place to ask and receive help in these cases is the *Yocto Project mailing lists*.

#### Nota

Using a library that no longer builds against the latest Yocto Project release and prints introspection related errors is a good candidate for the previous procedure.

## 8.22.2 Disabling the Generation of Introspection Data

You might find that you do not want to generate introspection data. Or, perhaps QEMU does not work on your build host and target architecture combination. If so, you can use either of the following methods to disable GIR file generations:

- Add the following to your distro configuration:

```
DISTRO_FEATURES_OPTED_OUT = "gobject-introspection-data"
```

Adding this statement disables generating introspection data using QEMU but will still enable building introspection tools and libraries (i.e. building them does not require the use of QEMU).

- Add the following to your machine configuration:

```
MACHINE_FEATURES_OPTED_OUT = "qemu-usermode"
```

Adding this statement disables the use of QEMU when building packages for your machine. Currently, this feature is used only by introspection recipes and has the same effect as the previously described option.

### Nota

Future releases of the Yocto Project might have other features affected by this option.

If you disable introspection data, you can still obtain it through other means such as copying the data from a suitable sysroot, or by generating it on the target hardware. The OpenEmbedded build system does not currently provide specific support for these techniques.

## 8.22.3 Testing that Introspection Works in an Image

Use the following procedure to test if generating introspection data is working in an image:

1. Make sure that "gobject-introspection-data" is not in `DISTRO_FEATURES_OPTED_OUT` and that "qemu-usermode" is not in `MACHINE_FEATURES_OPTED_OUT`.
2. Build `core-image-sato`.
3. Launch a Terminal and then start Python in the terminal.
4. Enter the following in the terminal:

```
>>> from gi.repository import GLib
>>> GLib.get_host_name()
```

5. For something a little more advanced, enter the following see: <https://python-gtk-3-tutorial.readthedocs.io/en/latest/introduction.html>

### 8.22.4 Known Issues

Here are known issues in GObject Introspection Support:

- `qemu-ppc64` immediately crashes. Consequently, you cannot build introspection data on that architecture.
- `x32` is not supported by QEMU. Consequently, introspection data is disabled.
- `musl` causes transient GLib binaries to crash on assertion failures. Consequently, generating introspection data is disabled.
- Because QEMU is not able to run the binaries correctly, introspection is disabled for some specific packages under specific architectures (e.g. `gcr`, `libsecret`, and `webkit`).
- QEMU usermode might not work properly when running 64-bit binaries under 32-bit host machines. In particular, "qemumips64" is known to not work under i686.

## 8.23 Optionally Using an External Toolchain

You might want to use an external toolchain as part of your development. If this is the case, the fundamental steps you need to accomplish are as follows:

- Understand where the installed toolchain resides. For cases where you need to build the external toolchain, you would need to take separate steps to build and install the toolchain.
- Make sure you add the layer that contains the toolchain to your `build/conf/bblayers.conf` file through the `BBLAYERS` variable.
- Set the `EXTERNAL_TOOLCHAIN` variable in your `build/conf/local.conf` file to the location in which you installed the toolchain (or in your distro *configuration file*).

The toolchain configuration is very flexible and customizable. It is primarily controlled with the `TCMODE` variable. This variable controls which `tcmode-*.inc` file to include from the `meta/conf/distro/include` directory within *OpenEmbedded-Core (OE-Core)*.

The default value of `TCMODE` is "default", which tells the OpenEmbedded build system to use its internally built toolchain (i.e. `tcmode-default.inc`). However, other patterns are accepted. In particular, "external-\*" refers to external toolchains. One example is the Mentor Graphics Sourcery G++ Toolchain. Support for this toolchain resides in the separate `meta-sourcery` layer at <https://github.com/MentorEmbedded/meta-sourcery/>. See its `README` file for details about how to use this layer.

Another example of external toolchain layer is `meta-arm-toolchain` supporting GNU toolchains released by ARM.

You can find further information by reading about the `TCMODE` variable in the Yocto Project Reference Manual's variable glossary.

## 8.24 Creating Partitioned Images Using Wic

Creating an image for a particular hardware target using the OpenEmbedded build system does not necessarily mean you can boot that image as is on your device. Physical devices accept and boot images in various ways depending on the specifics of the device. Usually, information about the hardware can tell you what image format the device requires.



Should your device require multiple partitions on an SD card, flash, or an HDD, you can use the OpenEmbedded Image Creator, Wic, to create the properly partitioned image.

The `wic` command generates partitioned images from existing OpenEmbedded build artifacts. Image generation is driven by partitioning commands contained in an OpenEmbedded kickstart file (`.wks`) specified either directly on the command line or as one of a selection of canned kickstart files as shown with the `wic list images` command in the "*Generate an Image using an Existing Kickstart File*" section. When you apply the command to a given set of build artifacts, the result is an image or set of images that can be directly written onto media and used on a particular system.

#### Nota

For a kickstart file reference, see the "*OpenEmbedded Kickstart (.wks) Reference*" Chapter in the Yocto Project Reference Manual.

The `wic` command and the infrastructure it is based on is by definition incomplete. The purpose of the command is to allow the generation of customized images, and as such, was designed to be completely extensible through a plugin interface. See the "*Using the Wic Plugin Interface*" section for information on these plugins.

This section provides some background information on Wic, describes what you need to have in place to run the tool, provides instruction on how to use the Wic utility, provides information on using the Wic plugins interface, and provides several examples that show how to use Wic.

### 8.24.1 Background

This section provides some background on the Wic utility. While none of this information is required to use Wic, you might find it interesting.

- The name "Wic" is derived from OpenEmbedded Image Creator (`oeic`). The "oe" diphthong in "oeic" was promoted to the letter "w", because "oeic" is both difficult to remember and to pronounce.
- Wic is loosely based on the Meego Image Creator (`mic`) framework. The Wic implementation has been heavily modified to make direct use of OpenEmbedded build artifacts instead of package installation and configuration, which are already incorporated within the OpenEmbedded artifacts.
- Wic is a completely independent standalone utility that initially provides easier-to-use and more flexible replacements for an existing functionality in OE-Core's *image-live* class. The difference between Wic and those examples is that with Wic the functionality of those scripts is implemented by a general-purpose partitioning language, which is based on Redhat kickstart syntax.

### 8.24.2 Requisiti

In order to use the Wic utility with the OpenEmbedded Build system, your system needs to meet the following requirements:

- Your environment and *Build Directory* must be ready, as if you were going to run `bitbake` commands. See *Initializing the Build Environment* for more details.
- Make the `wic` command-line tool available in your shell:
  1. Run the following command first:

```
$ bitbake wic-native -c addto_recipe_sysroot
```

2. Check if you can use the `wic` utility using `oe-run-native`:

```
$ oe-run-native wic-native wic --help
```

3. Define a local alias for the above command:

```
$ alias wic="oe-run-native wic-native wic"
```

This will make it possible to use `wic` from the *OpenEmbedded Build System* transparently below.

- You need to have the build artifacts already available, which typically means that you must have already created an image using the OpenEmbedded build system (e.g. `core-image-minimal`). While it might seem redundant to generate an image in order to create an image using Wic, the current version of Wic requires the artifacts in the form generated by the OpenEmbedded build system.
- Include "wic" as part of the *IMAGE\_FSTYPES* variable (from a *configuration file* or in the image recipe).
- Include the name of the *wic kickstart file* as part of the *WKS\_FILE* variable. If multiple candidate files can be provided by different layers, specify all the possible names through the *WKS\_FILES* variable instead.

These assignments are typically made in a machine *configuration file*.

### 8.24.3 Getting Help

You can get general help for the `wic` command by entering the `wic` command by itself or by entering the command with a `help` argument as follows:

```
$ wic -h
$ wic --help
$ wic help
```

Currently, Wic supports seven commands: `cp`, `create`, `help`, `list`, `ls`, `rm`, and `write`. You can get help for all these commands except "help" by using the following form:

```
$ wic help command
```

For example, the following command returns help for the `write` command:

```
$ wic help write
```

Wic supports help for three topics: `overview`, `plugins`, and `kickstart`. You can get help for any topic using the following form:

```
$ wic help topic
```

For example, the following returns overview help for Wic:

```
$ wic help overview
```

There is one additional level of help for Wic. You can get help on individual images through the `list` command. You can use the `list` command to return the available Wic images as follows:

```
$ wic list images
genericx86                Create an EFI disk image for
↳genericx86*
beaglebone-yocto          Create SD card image for Beaglebone
qemuriscv                 Create qcow2 image for RISC-V QEMU
↳machines
mkefidisk                 Create an EFI disk image
qemuloongarch             Create qcow2 image for LoongArch QEMU
↳machines
directdisk-multi-rootfs   Create multi rootfs image using
↳rootfs plugin
directdisk                Create a 'pcbios' direct disk image
efi-bootdisk
mkhybridiso               Create a hybrid ISO image
directdisk-gpt            Create a 'pcbios' direct disk image
systemd-bootdisk          Create an EFI disk image with systemd-
↳boot
sdimage-bootpart          Create SD card image with a boot
↳partition
qemux86-directdisk        Create a qemu machine 'pcbios' direct
↳disk image
directdisk-bootloader-config Create a 'pcbios' direct disk image
↳with custom bootloader config
```

Once you know the list of available Wic images, you can use `help` with the command to get help on a particular image. For example, the following command returns help on the "beaglebone-yocto" image:

```
$ wic list beaglebone-yocto help

Creates a partitioned SD card image for Beaglebone.
Boot files are located in the first vfat partition.
```

#### 8.24.4 Operational Modes

You can use Wic in two different modes, depending on how much control you need for specifying the OpenEmbedded build artifacts that are used for creating the image: Raw and Cooked:

- *Raw Mode:* You explicitly specify build artifacts through Wic command-line arguments.
- *Cooked Mode:* The current *MACHINE* setting and image name are used to automatically locate and provide the build artifacts. You just supply a kickstart file and the name of the image from which to use artifacts.

Regardless of the mode you use, you need to have the build artifacts ready and available.

## Raw Mode

Running Wic in raw mode allows you to specify all the partitions through the `wic` command line. The primary use for raw mode is if you have built your kernel outside of the Yocto Project *Build Directory*. In other words, you can point to arbitrary kernel, root filesystem locations, and so forth. Contrast this behavior with cooked mode where Wic looks in the *Build Directory* (e.g. `tmp/deploy/images/machine`).

The general form of the `wic` command in raw mode is:

```
$ wic create wks_file options ...
```

Where:

`wks_file`:

An OpenEmbedded kickstart file. You can provide your own custom file or use a file from a set of existing files as described by further options.

optional arguments:

```
-h, --help                show this help message and exit
-o OUTDIR, --outdir OUTDIR
                           name of directory to create image in
-e IMAGE_NAME, --image-name IMAGE_NAME
                           name of the image to use the artifacts from e.g. core-
                           image-sato
-r ROOTFS_DIR, --rootfs-dir ROOTFS_DIR
                           path to the /rootfs dir to use as the .wks rootfs
                           source
-b BOOTIMG_DIR, --bootimg-dir BOOTIMG_DIR
                           path to the dir containing the boot artifacts (e.g.
                           /EFI or /syslinux dirs) to use as the .wks bootimg
                           source
-k KERNEL_DIR, --kernel-dir KERNEL_DIR
                           path to the dir containing the kernel to use in the
                           .wks bootimg
-n NATIVE_SYSROOT, --native-sysroot NATIVE_SYSROOT
                           path to the native sysroot containing the tools to use
                           to build the image
-s, --skip-build-check
                           skip the build check
-f, --build-rootfs        build rootfs
-c {gzip,bzip2,xz}, --compress-with {gzip,bzip2,xz}
                           compress image with specified compressor
-m, --bmap                generate .bmap
```

(continues on next page)

(continua dalla pagina precedente)

```

--no-fstab-update    Do not change fstab file.
-v VARS_DIR, --vars VARS_DIR
                    directory with <image>.env files that store bitbake
                    variables
-D, --debug          output debug information

```

**i Nota**

You do not need root privileges to run Wic. In fact, you should not run as root when using the utility.

**Cooked Mode**

Running Wic in cooked mode leverages off artifacts in the *Build Directory*. In other words, you do not have to specify kernel or root filesystem locations as part of the command. All you need to provide is a kickstart file and the name of the image from which to use artifacts by using the "-e" option. Wic looks in the *Build Directory* (e.g. tmp/deploy/images/machine) for artifacts.

The general form of the wic command using Cooked Mode is as follows:

```
$ wic create wks_file -e IMAGE_NAME
```

Where:

wks\_file:

An OpenEmbedded kickstart file. You can provide your own custom file or use a file from a set of existing files provided with the Yocto Project release.

required argument:

```

-e IMAGE_NAME, --image-name IMAGE_NAME
                    name of the image to use the artifacts from e.g. core-
                    image-sato

```

**8.24.5 Using an Existing Kickstart File**

If you do not want to create your own kickstart file, you can use an existing file provided by the Wic installation. As shipped, kickstart files can be found in the *I Repository del Codice Sorgente di Yocto Project* in the following two locations:

```

meta-yocto/meta-yocto-bsp/files/wic
openembedded-core/files/wic

```

Use the following command to list the available kickstart files:

```
$ wic list images
genericx86                Create an EFI disk image for
↳genericx86*
beaglebone-yocto          Create SD card image for Beaglebone
qemuriscv                 Create qcow2 image for RISC-V QEMU
↳machines
mkefidisk                 Create an EFI disk image
qemuloongarch             Create qcow2 image for LoongArch QEMU
↳machines
directdisk-multi-rootfs   Create multi rootfs image using
↳rootfs plugin
directdisk                Create a 'pcbios' direct disk image
efi-bootdisk
mkhybridiso               Create a hybrid ISO image
directdisk-gpt            Create a 'pcbios' direct disk image
systemd-bootdisk         Create an EFI disk image with systemd-
↳boot
sdimage-bootpart          Create SD card image with a boot
↳partition
qemux86-directdisk        Create a qemu machine 'pcbios' direct
↳disk image
directdisk-bootloader-config Create a 'pcbios' direct disk image
↳with custom bootloader config
```

When you use an existing file, you do not have to use the `.wks` extension. Here is an example in Raw Mode that uses the `directdisk` file:

```
$ wic create directdisk -r rootfs_dir -b bootimg_dir \
    -k kernel_dir -n native_sysroot
```

Here are the actual partition language commands used in the `genericx86.wks` file to generate an image:

```
# short-description: Create an EFI disk image for genericx86*
# long-description: Creates a partitioned EFI disk image for genericx86* machines
part /boot --source bootimg_efi --sourceparams="loader=grub-efi" --ondisk sda --
↳label msdos --active --align 1024
part / --source rootfs --ondisk sda --fstype=ext4 --label platform --align 1024 --
↳use-uuid
part swap --ondisk sda --size 44 --label swap1 --fstype=swap

bootloader --ptable gpt --timeout=5 --append="rootfstype=ext4 console=ttyS0,115200
↳console=tty0"
```

## 8.24.6 Using the Wic Plugin Interface

You can extend and specialize Wic functionality by using Wic plugins. This section explains the Wic plugin interface.

### **Nota**

Wic plugins consist of "source" and "imager" plugins. Imager plugins are beyond the scope of this section.

Source plugins provide a mechanism to customize partition content during the Wic image generation process. You can use source plugins to map values that you specify using `--source` commands in kickstart files (i.e. `*.wks`) to a plugin implementation used to populate a given partition.

### **Nota**

If you use plugins that have build-time dependencies (e.g. native tools, bootloaders, and so forth) when building a Wic image, you need to specify those dependencies using the `WKS_FILE_DEPENDS` variable.

Source plugins are subclasses defined in plugin files. As shipped, the Yocto Project provides several plugin files. You can see the source plugin files that ship with the Yocto Project [here](#). Each of these plugin files contains source plugins that are designed to populate a specific Wic image partition.

Source plugins are subclasses of the `SourcePlugin` class, which is defined in the `openembedded-core/scripts/lib/wic/pluginbase.py` file. For example, the `BootimgEFIPlugin` source plugin found in the `bootimg_efi.py` file is a subclass of the `SourcePlugin` class, which is found in the `pluginbase.py` file.

You can also implement source plugins in a layer outside of the Source Repositories (external layer). To do so, be sure that your plugin files are located in a directory whose path is `scripts/lib/wic/plugins/source/` within your external layer. When the plugin files are located there, the source plugins they contain are made available to Wic.

When the Wic implementation needs to invoke a partition-specific implementation, it looks for the plugin with the same name as the `--source` parameter used in the kickstart file given to that partition. For example, if the partition is set up using the following command in a kickstart file:

```
part /boot --source bootimg_pcbios --ondisk sda --label boot --active --align 1024
```

The methods defined as class members of the matching source plugin (i.e. `bootimg_pcbios`) in the `bootimg_pcbios.py` plugin file are used.

To be more concrete, here is the corresponding plugin definition from the `bootimg_pcbios.py` file for the previous command along with an example method called by the Wic implementation when it needs to prepare a partition using an implementation-specific function:

```
class BootimgPcbiosPlugin(SourcePlugin):
```

(continues on next page)

(continua dalla pagina precedente)

```

"""
Create MBR boot partition and install syslinux on it.
"""

name = 'bootimg_pcbios'

    .
    .
    .

@classmethod
def do_prepare_partition(cls, part, source_params, creator, cr_workdir,
                        oe_builddir, bootimg_dir, kernel_dir,
                        rootfs_dir, native_sysroot):

    """
    Called to do the actual content population for a partition i.e. it
    'prepares' the partition to be incorporated into the image.
    In this case, prepare content for legacy bios boot partition.
    """

    .
    .
    .

```

If a subclass (plugin) itself does not implement a particular function, Wic locates and uses the default version in the superclass. It is for this reason that all source plugins are derived from the `SourcePlugin` class.

The `SourcePlugin` class defined in the `pluginbase.py` file defines a set of methods that source plugins can implement or override. Any plugins (subclass of `SourcePlugin`) that do not implement a particular method inherit the implementation of the method from the `SourcePlugin` class. For more information, see the `SourcePlugin` class in the `pluginbase.py` file for details:

The following list describes the methods implemented in the `SourcePlugin` class:

- `do_prepare_partition()`: Called to populate a partition with actual content. In other words, the method prepares the final partition image that is incorporated into the disk image.
- `do_configure_partition()`: Called before `do_prepare_partition()` to create custom configuration files for a partition (e.g. syslinux or grub configuration files).
- `do_install_disk()`: Called after all partitions have been prepared and assembled into a disk image. This method provides a hook to allow finalization of a disk image (e.g. writing an MBR).
- `do_stage_partition()`: Special content-staging hook called before `do_prepare_partition()`. This method is normally empty.

Typically, a partition just uses the passed-in parameters (e.g. the unmodified value of `bootimg_dir`). However, in some cases, things might need to be more tailored. As an example, certain files might additionally need to be taken from `bootimg_dir + /boot`. This hook allows those files to be staged in a customized fashion.



**i Nota**

`get_bitbake_var()` allows you to access non-standard variables that you might want to use for this behavior.

You can extend the source plugin mechanism. To add more hooks, create more source plugin methods within `SourcePlugin` and the corresponding derived subclasses. The code that calls the plugin methods uses the `plugin.get_source_plugin_methods()` function to find the method or methods needed by the call. Retrieval of those methods is accomplished by filling up a dict with keys that contain the method names of interest. On success, these will be filled in with the actual methods. See the Wic implementation for examples and details.

## 8.24.7 Wic Examples

This section provides several examples that show how to use the Wic utility. All the examples assume the list of requirements in the "*Requisiti*" section have been met. The examples assume the previously generated image is `core-image-minimal`.

### Generate an Image using an Existing Kickstart File

This example runs in Cooked Mode and uses the `mkefidisk` kickstart file:

```
$ wic create mkefidisk -e core-image-minimal
INFO: Building wic-tools...
.
.
.
INFO: The new image(s) can be found here:
./mkefidisk-201804191017-sda.direct

The following build artifacts were used to create the image(s):
  ROOTFS_DIR: /home/stephano/yocto/build/tmp-glibc/work/qemux86-
↳ oe-linux/core-image-minimal/1.0-r0/rootfs
  BOOTIMG_DIR: /home/stephano/yocto/build/tmp-glibc/work/qemux86-
↳ oe-linux/core-image-minimal/1.0-r0/recipe-sysroot/usr/share
  KERNEL_DIR: /home/stephano/yocto/build/tmp-glibc/deploy/images/
↳ qemux86
  NATIVE_SYSROOT: /home/stephano/yocto/build/tmp-glibc/work/i586-oe-
↳ linux/wic-tools/1.0-r0/recipe-sysroot-native

INFO: The image(s) were created using OE kickstart file:
/home/stephano/yocto/openembedded-core/files/wic/mkefidisk.wks
```

The previous example shows the easiest way to create an image by running in cooked mode and supplying a kickstart file and the "-e" option to point to the existing build artifacts (the "qemux86" machine is used here).

Once the image builds, the output provides image location, artifact use, and kickstart file information.

**i Nota**

You should always verify the details provided in the output to make sure that the image was indeed created exactly as expected.

Continuing with the example, you can now write the image from the [Build Directory](#) onto a USB stick, or whatever media for which you built your image, and boot from the media. You can write the image by using `bmaptool` or `dd`:

```
$ oe-run-native bmaptool-native bmaptool copy mkefidisk-201804191017-sda.direct /
↪dev/sdX
```

or :

```
$ sudo dd if=mkefidisk-201804191017-sda.direct of=/dev/sdX
```

**i Nota**

For more information on how to use the `bmaptool` to flash a device with an image, see the "[Flashing Images Using bmaptool](#)" section.

## Using a Modified Kickstart File

Because partitioned image creation is driven by the kickstart file, it is easy to affect image creation by changing the parameters in the file. This next example demonstrates that through modification of the `directdisk-gpt` kickstart file.

As mentioned earlier, you can use the command `wic list images` to show the list of existing kickstart files. The directory in which the `directdisk-gpt.wks` file resides is `files/wic`, which is located in [OpenEmbedded-Core \(OE-Core\)](#). Because available files reside in this directory, you can create and add your own custom files to the directory. Subsequent use of the `wic list images` command would then include your kickstart files.

In this example, the existing `directdisk-gpt` file already does most of what is needed. However, for the hardware in this example, the image will need to boot from `sdb` instead of `sda`, which is what the `directdisk-gpt` kickstart file uses.

The example begins by making a copy of the `directdisk-gpt.wks` file in the `files/wic` directory and then by changing the lines that specify the target disk from which to boot:

```
$ cp /home/stephano/yocto/openembedded-core/files/wic/directdisk-gpt.wks \
/home/stephano/yocto/openembedded-core/files/wic/directdisksdb-gpt.wks
```

Next, the example modifies the `directdisksdb-gpt.wks` file and changes all instances of `"--ondisk sda"` to `"--ondisk sdb"`. The example changes the following two lines and leaves the remaining lines untouched:

```
part /boot --source bootimg_pcbios --ondisk sdb --label boot --active --align 1024
part / --source rootfs --ondisk sdb --fstype=ext4 --label platform --align 1024 --
↪use-uuid
```

Once the lines are changed, the example generates the `directdisksdb-gpt` image. The command points the process at the `core-image-minimal` artifacts for the Next Unit of Computing (nuc) *MACHINE*:

```
$ wic create directdisksdb-gpt -e core-image-minimal
INFO: Building wic-tools...
.
.
.
Initialising tasks: 100% |#####| Time: 0:00:01
NOTE: Executing SetScene Tasks
NOTE: Executing RunQueue Tasks
NOTE: Tasks Summary: Attempted 1161 tasks of which 1157 didn't need to be rerun_
↪and all succeeded.
INFO: Creating image(s)...

INFO: The new image(s) can be found here:
./directdisksdb-gpt-201710090938-sdb.direct

The following build artifacts were used to create the image(s):
  ROOTFS_DIR: /home/stephano/yocto/build/tmp-glibc/work/qemux86-
↪oe-linux/core-image-minimal/1.0-r0/rootfs
  BOOTIMG_DIR: /home/stephano/yocto/build/tmp-glibc/work/qemux86-
↪oe-linux/core-image-minimal/1.0-r0/recipe-sysroot/usr/share
  KERNEL_DIR: /home/stephano/yocto/build/tmp-glibc/deploy/images/
↪qemux86
  NATIVE_SYSROOT: /home/stephano/yocto/build/tmp-glibc/work/i586-oe-
↪linux/wic-tools/1.0-r0/recipe-sysroot-native

INFO: The image(s) were created using OE kickstart file:
/home/stephano/yocto/openembedded-core/files/wic/directdisksdb-gpt.wks
```

Continuing with the example, you can now directly `dd` the image to a USB stick, or whatever media for which you built your image, and boot the resulting media:

```
$ sudo dd if=directdisksdb-gpt-201710090938-sdb.direct of=/dev/sdb
140966+0 records in
140966+0 records out
72174592 bytes (72 MB, 69 MiB) copied, 78.0282 s, 925 kB/s
$ sudo eject /dev/sdb
```

### Using a Modified Kickstart File and Running in Raw Mode

This next example manually specifies each build artifact (runs in Raw Mode) and uses a modified kickstart file. The example also uses the `-o` option to cause Wic to create the output somewhere other than the default output directory, which is the current directory:

```
$ wic create test.wks -o /home/stephano/testwic \
    --rootfs-dir /home/stephano/yocto/build/tmp/work/qemux86-poky-linux/core-
↪image-minimal/1.0-r0/rootfs \
    --bootimg-dir /home/stephano/yocto/build/tmp/work/qemux86-poky-linux/core-
↪image-minimal/1.0-r0/recipe-sysroot/usr/share \
    --kernel-dir /home/stephano/yocto/build/tmp/deploy/images/qemux86 \
    --native-sysroot /home/stephano/yocto/build/tmp/work/i586-poky-linux/wic-
↪tools/1.0-r0/recipe-sysroot-native

INFO: Creating image(s) ...

INFO: The new image(s) can be found here:
    /home/stephano/testwic/test-201710091445-sdb.direct

The following build artifacts were used to create the image(s):
    ROOTFS_DIR:                /home/stephano/yocto/build/tmp-glibc/work/qemux86-
↪oe-linux/core-image-minimal/1.0-r0/rootfs
    BOOTIMG_DIR:               /home/stephano/yocto/build/tmp-glibc/work/qemux86-
↪oe-linux/core-image-minimal/1.0-r0/recipe-sysroot/usr/share
    KERNEL_DIR:                /home/stephano/yocto/build/tmp-glibc/deploy/images/
↪qemux86
    NATIVE_SYSROOT:            /home/stephano/yocto/build/tmp-glibc/work/i586-oe-
↪linux/wic-tools/1.0-r0/recipe-sysroot-native

INFO: The image(s) were created using OE kickstart file:
    test.wks
```

For this example, *MACHINE* did not have to be specified since the artifact is manually specified.

## Using Wic to Manipulate an Image

Wic image manipulation allows you to shorten turnaround time during image development. For example, you can use Wic to delete the kernel partition of a Wic image and then insert a newly built kernel. This saves you time from having to rebuild the entire image each time you modify the kernel.

### Nota

In order to use Wic to manipulate a Wic image as in this example, your development machine must have the `mttools` package installed.

The following example examines the contents of the Wic image, deletes the existing kernel, and then inserts a new kernel:

1. *List the Partitions:* Use the `wic ls` command to list all the partitions in the Wic image:

```
$ wic ls tmp/deploy/images/qemux86/core-image-minimal-qemux86.wic
```

| Num | Start    | End      | Size     | Fstype |
|-----|----------|----------|----------|--------|
| 1   | 1048576  | 25041919 | 23993344 | fat16  |
| 2   | 25165824 | 72157183 | 46991360 | ext4   |

The previous output shows two partitions in the `core-image-minimal-qemux86.wic` image.

2. *Examine a Particular Partition:* Use the `wic ls` command again but in a different form to examine a particular partition.

#### Nota

You can get command usage on any Wic command using the following form:

```
$ wic help command
```

For example, the following command shows you the various ways to use the `wic ls` command:

```
$ wic help ls
```

The following command shows what is in partition one:

```
$ wic ls tmp/deploy/images/qemux86/core-image-minimal-qemux86.wic:1
Volume in drive : is boot
Volume Serial Number is E894-1809
Directory for ::/

libcom32 c32      186500 2017-10-09  16:06
libutil  c32      24148 2017-10-09  16:06
syslinux cfg      220 2017-10-09  16:06
vesamenu c32      27104 2017-10-09  16:06
vmlinuz          6904608 2017-10-09  16:06
5 files              7 142 580 bytes
16 582 656 bytes free
```

The previous output shows five files, with the `vmlinuz` being the kernel.

#### Nota

If you see the following error, you need to update or create a `~/.mtoolsrc` file and be sure to have the line `"mtools_skip_check=1"` in the file. Then, run the Wic command again:

```
ERROR: _exec_cmd: /usr/bin/mkdir -i /tmp/wic-parttfokuwra ::/ returned '1'
↳ instead of 0
output: Total number of sectors (47824) not a multiple of sectors per
↳ track (32)!
Add mtools_skip_check=1 to your .mtoolsrc file to skip this test
```

3. *Remove the Old Kernel:* Use the `wic rm` command to remove the `vmlinuz` file (kernel):

```
$ wic rm tmp/deploy/images/qemux86/core-image-minimal-qemux86.wic:1/vmlinuz
```

4. *Add In the New Kernel:* Use the `wic cp` command to add the updated kernel to the Wic image. Depending on how you built your kernel, it could be in different places. If you used `devtool` and an SDK to build your kernel, it resides in the `tmp/work` directory of the extensible SDK. If you used `make` to build the kernel, the kernel will be in the `workspace/sources` area.

The following example assumes `devtool` was used to build the kernel:

```
$ wic cp poky_sdk/tmp/work/qemux86-poky-linux/linux-yocto/4.12.12+git999-r0/
↳ linux-yocto-4.12.12+git999/arch/x86/boot/bzImage \
    build/tmp/deploy/images/qemux86/core-image-minimal-qemux86.wic:1/
↳ vmlinuz
```

Once the new kernel is added back into the image, you can use the `dd` command or *`bmaptool`* commands to flash your wic image onto an SD card or USB stick and test your target.

#### **i** Nota

Using *`bmaptool`* is generally 10 to 20 times faster than using `dd`.

## 8.25 Flashing Images Using *`bmaptool`*

A fast and easy way to flash an image to a bootable device is to use *`bmaptool`*, which is integrated into the OpenEmbedded build system. *`bmaptool`* is a generic tool that creates a file's block map (bmap) and then uses that map to copy the file. As compared to traditional tools such as `dd` or `cp`, *`bmaptool`* can copy (or flash) large files like raw system image files much faster.

#### **i** Nota

- If you are using Ubuntu or Debian distributions, you can install the *`bmaptool`* package using the following command and then use the tool without specifying `PATH` even from the root account:

```
$ sudo apt install bmaptool
```

- If you are unable to install the *`bmaptool`* package, you will need to build *`bmaptool`* before using it. Use the following command:

```
$ bitbake bmaptool-native -caddto_recipe_sysroot
```

Following, is an example that shows how to flash a Wic image. Realize that while this example uses a Wic image, you can use *`bmaptool`* to flash any type of image. Use these steps to flash an image using *`bmaptool`*:

1. *Update your image types:* You need to have the *`IMAGE_FSTYPES`* set in image recipe, distro *configuration file* or *`build/conf/local.conf`* file before building your image:

```
IMAGE_FSTYPES += "wic wic.bmap"
```

2. *Get Your Image:* Either have your image ready (pre-built with the *IMAGE\_FSTYPES* setting previously mentioned) or take the step to build the image:

```
$ bitbake image
```

3. *Flash the Device:* Flash the device with the image by using *bmaptool* depending on your particular setup. The following commands assume the image resides in the *Build Directory*'s `deploy/images/` area:

- If you installed the package for *bmaptool*, you can directly run:

```
$ sudo bmaptool copy build-directory/tmp/deploy/images/machine/image.wic /  
↪ dev/sdX
```

- Otherwise, if you built *bmaptool* with BitBake, run:

```
$ sudo chmod a+w /dev/sdX      # get write access to the media, needed  
↪ only once after booting  
$ oe-run-native bmaptool-native bmaptool copy build-directory/tmp/deploy/  
↪ images/machine/image.wic /dev/sdX
```

For help on the *bmaptool* command, use the following command:

```
$ bmaptool --help
```

### Nota

Earlier releases of Ubuntu and Debian had a package named `bmap-tools`; you can still install by this name as this is simply a transitional package which exists solely to ensure backward compatibility and smooth upgrades from older installations.

## 8.26 Creating Your Own Distribution

When you build an image using the Yocto Project and follow the default setup showcased in *Setting Up to Use the Yocto Project*, you are using the *Poky* reference distribution.

Poky is explicitly a *reference* distribution for testing and development purposes. It enables most hardware and software features so that they can be tested, but this also means that from a security point of view the attack surface is very large. Additionally, at some point it is likely that you will want to gain more control over package alternative selections, compile-time options, and other low-level configurations. For both of these reasons, if you are using the Yocto Project for production use then you are strongly encouraged to create your own distribution.

To create your own distribution, the basic steps consist of creating your own distribution layer, creating your own distribution configuration file, and then adding any needed code and Metadata to the layer. The following steps provide some more detail:

- *Create a layer for your new distro:* Create your distribution layer so that you can keep your Metadata and code for the distribution separate. It is strongly recommended that you create and use your own layer for configuration and code. Using your own layer as compared to just placing configurations in a `build/conf/local.conf` configuration file makes it easier to reproduce the same build configuration when using multiple build machines. See the "*Creating Your Own Layer*" section for information on how to quickly set up a layer.
- *Create the distribution configuration file:* The distribution configuration file needs to be created in the `conf/distro` directory of your layer. You need to name it using your distribution name (e.g. `mydistro.conf`).

#### Nota

The `DISTRO` variable in your `build/conf/local.conf` file determines the name of your distribution. You can also use the `distro/` configuration fragment.

You can split out parts of your configuration file into include files and then "require" them from within your distribution configuration file. Be sure to place the include files in the `conf/distro/include` directory of your layer. A common example usage of include files would be to separate out the selection of desired version and revisions for individual recipes.

Your configuration file needs to set the following required variables:

- `DISTRO_NAME`
- `DISTRO_VERSION`

These following variables are optional and you typically set them from the distribution configuration file:

- `DISTRO_FEATURES`
- `DISTRO_EXTRA_RDEPENDS`
- `DISTRO_EXTRA_RRECOMMENDS`
- `TCLIBC`

#### Suggerimento

If you want to base your distribution configuration file on the very basic configuration from OE-Core, you can use `conf/distro/defaultsetup.conf` as a reference and just include variables that differ as compared to `defaultsetup.conf`. Alternatively, you can create a distribution configuration file from scratch using the `defaultsetup.conf` file or configuration files from another distribution such as Poky as a reference.

- *Provide miscellaneous variables:* Be sure to define any other variables for which you want to create a default or enforce as part of the distribution configuration. You can include nearly any variable from the `build/conf/local.conf` file. The variables you use are not limited to the list in the previous bulleted item.
- *Point to Your distribution configuration file:* In your `build/conf/local.conf` file in the *Build Directory*, set your `DISTRO` variable to point to your distribution's configuration file. For example, if your distribution's configuration file is named `mydistro.conf`, then you point to it as follows:



```
DISTRO = "mydistro"
```

You can also set the *distro/* configuration fragment from the command-line.

- *Add more to the layer if necessary:* Use your layer to hold other information needed for the distribution:
  - Add recipes for installing distro-specific configuration files that are not already installed by another recipe. If you have distro-specific configuration files that are included by an existing recipe, you should add an append file ( `.bbappend`) for those. For general information and recommendations on how to add recipes to your layer, see the *"Creating Your Own Layer"* and *"Following Best Practices When Creating Layers"* sections.
  - Add any image recipes that are specific to your distribution.
  - Add a `psplash` append file for a branded splash screen, using the `SPLASH_IMAGES` variable.
  - Add any other append files to make custom changes that are specific to individual recipes.

For information on append files, see the *"Appending Other Layers Metadata With Your Layer"* section.

### 8.26.1 Copying and modifying the Poky distribution

Instead of creating a custom distribution from scratch as per above, you may wish to start your custom distribution configuration by copying the Poky distribution provided within the `meta-poky` layer and then modifying it. This is fine, however if you do this you should keep the following in mind:

- Every reference to Poky needs to be updated in your copy so that it will still apply. This includes override usage within files (e.g. `:poky`) and in directory names. This is a good opportunity to evaluate each one of these customizations to see if they are needed for your use case.
- Unless you also intend to use them, the `poky-tiny`, `poky-altcfg` and `poky-bleeding` variants and any references to them can be removed.
- More generally, the Poky distribution configuration enables a lot more than you likely need for your production use case. You should evaluate *every* configuration choice made in your copy to determine if it is needed.

## 8.27 Creating a Custom Template Configuration Directory

If you are producing your own customized version of the build system for use by other users, you might want to provide a custom build configuration that includes all the necessary settings and layers (i.e. *build/conf/local.conf* and *build/conf/bblayers.conf* that are created in a new *Build Directory*) and a custom message that is shown when setting up the build. This can be done by creating one or more template configuration directories in your custom distribution layer.

This can be done by using `bitbake-layers save-build-conf`:

```
$ bitbake-layers save-build-conf ../../meta-alex/ test-1
NOTE: Starting bitbake server...
NOTE: Configuration template placed into /srv/bitbake-builds/layers/meta-alex/conf/
      ↪ templates/test-1
```

(continues on next page)

(continua dalla pagina precedente)

```
Please review the files in there, and particularly provide a configuration.
↪description in /srv/bitbake-builds/meta-alex/conf/templates/test-1/conf-notes.txt
You can try out the configuration with
TEMPLATECONF=/srv/bitbake-builds/layers/meta-alex/conf/templates/test-1 . /srv/
↪bitbake-builds/layers/openembedded-core/oe-init-build-env build-try-test-1
```

The above command takes the config files from the currently active *Build Directory* under `conf`, replaces site-specific paths in *build/conf/bblayers.conf* with `##OECORE##`-relative paths, and copies the config files into a specified layer under a specified template name.

To use those saved templates as a starting point for a build, users should point to one of them with *TEMPLATECONF* environment variable:

```
TEMPLATECONF=/srv/bitbake-builds/layers/meta-alex/conf/templates/test-1 . /srv/
↪bitbake-builds/layers/openembedded-core/oe-init-build-env build-try-test-1
```

The OpenEmbedded build system uses the environment variable *TEMPLATECONF* to locate the directory from which it gathers configuration information that ultimately ends up in the *Build Directory* `conf` directory.

If *TEMPLATECONF* is not set, the default value is obtained from `.templateconf` file that is read from the same directory as `oe-init-build-env` script. For the Poky reference distribution this would be:

```
TEMPLATECONF=${TEMPLATECONF:-meta/conf/templates/default}
```

If you look at a configuration template directory, you will see the `bblayers.conf.sample`, `local.conf.sample`, `conf-summary.txt` and `conf-notes.txt` files. The build system uses these files to form the respective *build/conf/bblayers.conf* file, `local.conf` file, and show users usage information about the build they're setting up when running the `oe-init-build-env` setup script. These can be edited further if needed to improve or change the build configurations available to the users, and provide useful summaries and detailed usage notes.

## 8.28 Conserving Disk Space

### 8.28.1 Conserving Disk Space During Builds

To help conserve disk space during builds, you can add the following statement to your project's *build/conf/local.conf* configuration file found in the *Build Directory*:

```
INHERIT += "rm_work"
```

Adding this statement deletes the work directory used for building a recipe once the recipe is built. For more information on `"rm_work"`, see the *rm\_work* class in the Yocto Project Reference Manual.

When you inherit this class and build a `core-image-sato` image for a `qemux86-64` machine from an Ubuntu 22.04 x86-64 system, you end up with a final disk usage of 22 Gbytes instead of 140 Gbytes. However, 40 Gbytes of initial free disk space are still needed to create temporary files before they can be deleted.

## 8.28.2 Purging Obsolete Shared State Cache Files

After multiple build iterations, the Shared State (sstate) cache can contain multiple cache files for a given package, consuming a substantial amount of disk space. However, only the most recent ones are likely to be reused.

The following command is a quick way to purge all the cache files which haven't been used for a least a specified number of days:

```
find build/sstate-cache -type f -mtime +$DAYS -delete
```

The above command relies on the fact that BitBake touches the sstate cache files as it accesses them, when it has write access to the cache.

You could use `-atime` instead of `-mtime` if the partition isn't mounted with the `noatime` option for a read only cache.

For more advanced needs, OpenEmbedded-Core also offers a more elaborate command. It has the ability to purge all but the newest cache files on each architecture, and also to remove files that it considers unreachable by exploring a set of build configurations. However, this command requires a full build environment to be available and doesn't work well covering multiple releases. It won't work either on limited environments such as BSD based NAS:

```
sstate-cache-management.py --remove-duplicated --cache-dir=sstate-cache
```

This command will ask you to confirm the deletions it identifies. Run `sstate-cache-management.py` for more details about this script.

### Nota

As this command is much more cautious and selective, removing only cache files, it will execute much slower than the simple `find` command described above. Therefore, it may not be your best option to trim huge cache directories.

## 8.29 Working with Packages

This section describes a few tasks that involve packages:

- *Excluding Packages from an Image*
- *Incrementing a Package Version*
- *Handling Optional Module Packaging*
- *Using Runtime Package Management*
- *Generating and Using Signed Packages*
- *Setting up and running package test (ptest)*
- **(disabled)** *Creating Node Package Manager (NPM) Packages*
- *Adding custom metadata to packages*

### 8.29.1 Excluding Packages from an Image

You might find it necessary to prevent specific packages from being installed into an image. If so, you can use several variables to direct the build system to essentially ignore installing recommended packages or to not install a package at all.

The following list introduces variables you can use to prevent packages from being installed into your image. Each of these variables only works with IPK and RPM package types, not for Debian packages. Also, you can use these variables in a distro *configuration file* or attach them to a specific image recipe by using a recipe name override. For more detail on the variables, see the descriptions in the Yocto Project Reference Manual's glossary chapter.

- ***BAD\_RECOMMENDATIONS***: Use this variable to specify "recommended-only" packages that you do not want installed.
- ***NO\_RECOMMENDATIONS***: Use this variable to prevent all "recommended-only" packages from being installed.
- ***PACKAGE\_EXCLUDE***: Use this variable to prevent specific packages from being installed regardless of whether they are "recommended-only" or not. You need to realize that the build process could fail with an error when you prevent the installation of a package whose presence is required by an installed package.

### 8.29.2 Incrementing a Package Version

This section provides some background on how binary package versioning is accomplished and presents some of the services, variables, and terminology involved.

In order to understand binary package versioning, you need to consider the following:

- **Binary Package**: The binary package that is eventually built and installed into an image.
- **Binary Package Version**: The binary package version is composed of two components --- a version and a revision.

#### Nota

Technically, a third component, the "epoch" (i.e. *PE*) is involved but this discussion for the most part ignores *PE*.

The version and revision are taken from the *PV* and *PR* variables, respectively.

- ***PV***: The recipe version. *PV* represents the version of the software being packaged. Do not confuse *PV* with the binary package version.
- ***PR***: The recipe revision.
- ***PR Service***: A network-based service that helps automate keeping package feeds compatible with existing package manager applications such as RPM, APT, and OPKG.

Whenever the binary package content changes, the binary package version must change. Changing the binary package version is accomplished by changing or "bumping" the *PR* and/or *PV* values. Increasing these values occurs one of two ways:

- Automatically using a Package Revision Service (PR Service).

- Manually incrementing the *PR* and/or *PV* variables.

Given a primary challenge of any build system and its users is how to maintain a package feed that is compatible with existing package manager applications such as RPM, APT, and OPKG, using an automated system is much preferred over a manual system. In either system, the main requirement is that binary package version numbering increases in a linear fashion and that there is a number of version components that support that linear progression. For information on how to ensure package revisioning remains linear, see the "*Automatically Incrementing a Package Version Number*" section.

The following three sections provide related information on the PR Service, the manual method for "bumping" *PR* and/or *PV*, and on how to ensure binary package revisioning remains linear.

### Working With a PR Service

As mentioned, attempting to maintain revision numbers in the *Metadata* is error prone, inaccurate, and causes problems for people submitting recipes. Conversely, the PR Service automatically generates increasing numbers, particularly the revision field, which removes the human element.

#### Nota

For additional information on using a PR Service, you can see the [PR Service](#) wiki page.

The Yocto Project uses variables in order of decreasing priority to facilitate revision numbering (i.e. *PE*, *PV*, and *PR* for epoch, version, and revision, respectively). The values are highly dependent on the policies and procedures of a given distribution and package feed.

Because the OpenEmbedded build system uses "*signatures*", which are unique to a given build, the build system knows when to rebuild packages. All the inputs into a given task are represented by a signature, which can trigger a rebuild when different. Thus, the build system itself does not rely on the *PR*, *PV*, and *PE* numbers to trigger a rebuild. The signatures, however, can be used to generate these values.

The PR Service works with both `OEBasic` and `OEBasicHash` generators. The value of *PR* bumps when the checksum changes and the different generator mechanisms change signatures under different circumstances.

As implemented, the build system includes values from the PR Service into the *PR* field as an addition using the form ".x" so `r0` becomes `r0.1`, `r0.2` and so forth. This scheme allows existing *PR* values to be used for whatever reasons, which include manual *PR* bumps, should it be necessary.

By default, the PR Service is not enabled or running. Thus, the packages generated are just "self consistent". The build system adds and removes packages and there are no guarantees about upgrade paths but images will be consistent and correct with the latest changes.

The simplest form for a PR Service is for a single host development system that builds the package feed (building system). For this scenario, you can enable a local PR Service by setting `PRSERV_HOST` in your `build/conf/local.conf` file in the *Build Directory*:

```
PRSERV_HOST = "localhost:0"
```

Once the service is started, packages will automatically get increasing *PR* values and BitBake takes care of starting and stopping the server.

If you have a more complex setup where multiple host development systems work against a common, shared package feed, you have a single PR Service running and it is connected to each building system. For this scenario, you need to start the PR Service using the `bitbake-prserv` command:

```
bitbake-prserv --host ip --port port --start
```

In addition to hand-starting the service, you need to update the `build/conf/local.conf` file of each building system as described earlier so each system points to the server and port.

It is also recommended you use build history, which adds some sanity checks to binary package versions, in conjunction with the server that is running the PR Service. To enable build history, add the following to each building system's `build/conf/local.conf` file (or set this in your distro *configuration file*):

```
# It is recommended to activate "buildhistory" for testing the PR service
INHERIT += "buildhistory"
BUILDHISTORY_COMMIT = "1"
```

For information on build history, see the "*Maintaining Build Output Quality with buildhistory*" section.

#### Nota

The OpenEmbedded build system does not maintain *PR* information as part of the shared state (sstate) packages. If you maintain an sstate feed, it's expected that either all your building systems that contribute to the sstate feed use a shared PR service, or you do not run a PR service on any of your building systems.

That's because if you had multiple machines sharing a PR service but not their sstate feed, you could end up with "diverging" hashes for the same output artefacts. When presented to the share PR service, each would be considered as new and would increase the revision number, causing many unnecessary package upgrades.

For more information on shared state, see the "*Cache di Shared State*" section in the Yocto Project Overview and Concepts Manual.

## Manually Bumping PR

The alternative to setting up a PR Service is to manually "bump" the *PR* variable.

If a committed change results in changing the package output, then the value of the *PR* variable needs to be increased (or "bumped") as part of that commit. For new recipes you should add the *PR* variable and set its initial value equal to "r0", which is the default. Even though the default value is "r0", the practice of adding it to a new recipe makes it harder to forget to bump the variable when you make changes to the recipe in future.

Usually, version increases occur only to binary packages. However, if for some reason *PV* changes but does not increase, you can increase the *PE* variable (Package Epoch). The *PE* variable defaults to "0".

Binary package version numbering strives to follow the [Debian Version Field Policy Guidelines](#). These guidelines define how versions are compared and what "increasing" a version means.

## Automatically Incrementing a Package Version Number

When fetching a repository, BitBake uses the `SRCREV` variable to determine the specific source code revision from which to build. You set the `SRCREV` variable to `AUTOREV` to cause the OpenEmbedded build system to automatically use the latest revision of the software:

```
SRCREV = "${AUTOREV}"
```

Furthermore, you need to include a + sign in `PV` in order to automatically update the version whenever the revision of the source code changes. Here is an example:

```
PV = "1.0+git"
```

The OpenEmbedded build system will automatically add the source control information to the end of the variable `PKGVS`, in this format:

```
AUTOINC+source_code_revision
```

The build system replaces the `AUTOINC` with a number. The number used depends on the state of the PR Service:

- If PR Service is enabled, the build system increments the number, which is similar to the behavior of `PR`. This behavior results in linearly increasing package versions, which is desirable. Here is an example:

```
hello-world-git_1.0+git0+b6558dd387-r0.0_armv7a-neon.ipk
hello-world-git_1.0+git1+dd2f5c3565-r0.1_armv7a-neon.ipk
```

Two numbers got incremented here:

- `gitX` changed from `git0` to `git1`. This is because there was a change in the source code (`SRCREV`).
- `r0.X` changed from `r0.0` to `r0.1`. This is because the hash of the `do_package` task changed.

The reason for this change can be many. To understand why the hash of the `do_package` task changed, you can run the following command:

```
$ bitbake-diffsigs -t hello-world package
```

- If PR Service is not enabled, the build system replaces the `AUTOINC` placeholder with zero (i.e. "0"). This results in changing the package version since the source revision is included. However, package versions are not increased linearly. Here is an example:

```
hello-world-git_1.0+git0+b6558dd387-r0_armv7a-neon.ipk
hello-world-git_1.0+git0+dd2f5c3565-r0_armv7a-neon.ipk
```

In summary, the OpenEmbedded build system does not track the history of binary package versions for this purpose. `AUTOINC`, in this case, is comparable to `PR`. If PR server is not enabled, `AUTOINC` in the package version is simply replaced by "0". If PR server is enabled, the build system keeps track of the package versions and bumps the number when the package revision changes.

### 8.29.3 Handling Optional Module Packaging

Many pieces of software split functionality into optional modules (or plugins) and the plugins that are built might depend on configuration options. To avoid having to duplicate the logic that determines what modules are available in your recipe or to avoid having to package each module by hand, the OpenEmbedded build system provides functionality to handle module packaging dynamically.

To handle optional module packaging, you need to do two things:

- Ensure the module packaging is actually done.
- Ensure that any dependencies on optional modules from other recipes are satisfied by your recipe.

#### Making Sure the Packaging is Done

To ensure the module packaging actually gets done, you use the `do_split_packages` function within the `populate_packages` Python function in your recipe. The `do_split_packages` function searches for a pattern of files or directories under a specified path and creates a package for each one it finds by appending to the `PACKAGES` variable and setting the appropriate values for `FILES:packagename`, `RDEPENDS:packagename`, `DESCRIPTION:packagename`, and so forth. Here is an example from the `lighttpd` recipe:

```
python populate_packages:prepend () {
    lighttpd_libdir = d.expand('${libdir}')
    do_split_packages(d, lighttpd_libdir, '^mod_(.*)\.so$',
                     'lighttpd-module-%s', 'Lighttpd module for %s',
                     extra_depends='')
}
```

The previous example specifies a number of things in the call to `do_split_packages`.

- A directory within the files installed by your recipe through *do\_install* in which to search.
- A regular expression used to match module files in that directory. In the example, note the parentheses () that mark the part of the expression from which the module name should be derived.
- A pattern to use for the package names.
- A description for each package.
- An empty string for `extra_depends`, which disables the default dependency on the main `lighttpd` package. Thus, if a file in `${libdir}` called `mod_alias.so` is found, a package called `lighttpd-module-alias` is created for it and the *DESCRIPTION* is set to "Lighttpd module for alias".

Often, packaging modules is as simple as the previous example. However, there are more advanced options that you can use within `do_split_packages` to modify its behavior. And, if you need to, you can add more logic by specifying a hook function that is called for each package. It is also perfectly acceptable to call `do_split_packages` multiple times if you have more than one set of modules to package.

For more examples that show how to use `do_split_packages`, see the `connman.inc` file in the `meta/recipes-connectivity/connman/` directory of *OpenEmbedded-Core (OE-Core)*. You can also find examples in `meta/classes-recipe/kernel.bbclass`.

Here is a reference that shows `do_split_packages` mandatory and optional arguments:



**Mandatory arguments****root**

The path in which to search

**file\_regex**

Regular expression to match searched files.

Use parentheses () to mark the part of this expression that should be used to derive the module name (to be substituted where %s is used in other function arguments as noted below)

**output\_pattern**

Pattern to use for the package names. Must include %s.

**description**

Description to set for each package. Must include %s.

**Optional arguments****postinst**

Postinstall script to use for all packages (as a string)

**recursive**

True to perform a recursive search --- default  
False

**hook**

A hook function to be called for every match. The function will be called with the following arguments (in the order listed):

**f**

Full path to the file/directory match

**pkg**

The package name

**file\_regex**

As above

**output\_pattern**

As above

**modulename**

The module name derived using file\_regex

**extra\_depends**

Extra runtime dependencies (RDEPENDS) to be set for all packages. The default value of None causes a dependency on the main package

(continues on next page)

(continua dalla pagina precedente)

```

    (${PN}) --- if you do not want this, pass empty
    string '' for this parameter.
aux_files_pattern
    Extra item(s) to be added to FILES for each
    package. Can be a single string item or a list
    of strings for multiple items. Must include %s.
postrm
    postrm script to use for all packages (as a
    string)
allow_dirs
    True to allow directories to be matched -
    default False
prepend
    If True, prepend created packages to PACKAGES
    instead of the default False which appends them
match_path
    match file_regex on the whole relative path to
    the root rather than just the filename
aux_files_pattern_verbatim
    Extra item(s) to be added to FILES for each
    package, using the actual derived module name
    rather than converting it to something legal
    for a package name. Can be a single string item
    or a list of strings for multiple items. Must
    include %s.
allow_links
    True to allow symlinks to be matched --- default
    False
summary
    Summary to set for each package. Must include %s;
    defaults to description if not set.

```

## Satisfying Dependencies

The second part for handling optional module packaging is to ensure that any dependencies on optional modules from other recipes are satisfied by your recipe. You can be sure these dependencies are satisfied by using the *PACKAGES\_DYNAMIC* variable. Here is an example that continues with the `lighttpd` recipe shown earlier:

```
PACKAGES_DYNAMIC = "lighttpd-module-.*"
```

The name specified in the regular expression can of course be anything. In this example, it is `lighttpd-module-` and is specified as the prefix to ensure that any *RDEPENDS* and *RRECOMMENDS* on a package name starting with the prefix are satisfied during build time. If you are using `do_split_packages` as described in the previous section, the value you put in *PACKAGES\_DYNAMIC* should correspond to the name pattern specified in the call to

`do_split_packages`.

## 8.29.4 Using Runtime Package Management

During a build, BitBake always transforms a recipe into one or more packages. For example, BitBake takes the `bash` recipe and produces a number of packages (e.g. `bash`, `bash-bashbug`, `bash-completion`, `bash-completion-dbg`, `bash-completion-dev`, `bash-completion-extra`, `bash-dbg`, and so forth). Not all generated packages are included in an image.

In several situations, you might need to update, add, remove, or query the packages on a target device at runtime (i.e. without having to generate a new image). Examples of such situations include:

- You want to provide in-the-field updates to deployed devices (e.g. security updates).
- You want to have a fast turn-around development cycle for one or more applications that run on your device.
- You want to temporarily install the "debug" packages of various applications on your device so that debugging can be greatly improved by allowing access to symbols and source debugging.
- You want to deploy a more minimal package selection of your device but allow in-the-field updates to add a larger selection for customization.

In all these situations, you have something similar to a more traditional Linux distribution in that in-field devices are able to receive pre-compiled packages from a server for installation or update. Being able to install these packages on a running, in-field device is what is termed "runtime package management".

In order to use runtime package management, you need a host or server machine that serves up the pre-compiled packages plus the required metadata. You also need package manipulation tools on the target. The build machine is a likely candidate to act as the server. However, that machine does not necessarily have to be the package server. The build machine could push its artifacts to another machine that acts as the server (e.g. Internet-facing). In fact, doing so is advantageous for a production environment as getting the packages away from the development system's *Build Directory* prevents accidental overwrites.

A simple build that targets just one device produces more than one package database. In other words, the packages produced by a build are separated out into a couple of different package groupings based on criteria such as the target's CPU architecture, the target board, or the C library used on the target. For example, a build targeting the `qemux86` device produces the following three package databases: `noarch`, `i586`, and `qemux86`. If you wanted your `qemux86` device to be aware of all the packages that were available to it, you would need to point it to each of these databases individually. In a similar way, a traditional Linux distribution usually is configured to be aware of a number of software repositories from which it retrieves packages.

Using runtime package management is completely optional and not required for a successful build or deployment in any way. But if you want to make use of runtime package management, you need to do a couple things above and beyond the basics. The remainder of this section describes what you need to do.

### Build Considerations

This section describes build considerations of which you need to be aware in order to provide support for runtime package management.

When BitBake generates packages, it needs to know what format or formats to use. In your configuration, you use the `PACKAGE_CLASSES` variable to specify the format:

#. Select the desired package format as follows from your *build/conf/local.conf* or distro *configuration file*:

```
PACKAGE_CLASSES ?= "package_packageformat"
```

where `packageformat` can be `"ipk"`, `"rpm"`, or `"deb"` which are the supported package formats.

.. note::

Because the Yocto Project supports three different package formats, you can set the variable with more than one argument. However, the OpenEmbedded build system only uses the first argument when creating an image or Software Development Kit (SDK).

If you would like your image to start off with a basic package database containing the packages in your current build as well as to have the relevant tools available on the target for runtime package management, you can include `"package-management"` in the *IMAGE\_FEATURES* variable. Including `"package-management"` in this configuration variable ensures that when the image is assembled for your target, the image includes the currently-known package databases as well as the target-specific tools required for runtime package management to be performed on the target. However, this is not strictly necessary. You could start your image off without any databases but only include the required on-target package tool(s). As an example, you could include `"opkg"` in your *IMAGE\_INSTALL* variable if you are using the IPK package format. You can then initialize your target's package database(s) later once your image is up and running.

Whenever you perform any sort of build step that can potentially generate a package or modify existing package, it is always a good idea to re-generate the package index after the build by using the following command:

```
$ bitbake package-index
```

It might be tempting to build the package and the package index at the same time with a command such as the following:

```
$ bitbake some-package package-index
```

Do not do this as BitBake does not schedule the package index for after the completion of the package you are building. Consequently, you cannot be sure of the package index including information for the package you just built. Thus, be sure to run the package update step separately after building any packages.

You can use the *PACKAGE\_FEED\_ARCHS*, *PACKAGE\_FEED\_BASE\_PATHS*, and *PACKAGE\_FEED\_URIS* variables to pre-configure target images to use a package feed. If you do not define these variables, then manual steps as described in the subsequent sections are necessary to configure the target. You should set these variables before building the image in order to produce a correctly configured image.

#### Nota

Your image will need enough free storage space to run package upgrades, especially if many of them need to be downloaded at the same time. You should make sure images are created with enough free space by setting the `IMAGE_ROOTFS_EXTRA_SPACE` variable.

When your build is complete, your packages reside in the `${TMPDIR}/deploy/packageformat` directory. For example, if `${TMPDIR}` is `tmp` and your selected package type is RPM, then your RPM packages are available in `tmp/deploy/rpm`.

## Host or Server Machine Setup

Although other protocols are possible, a server using HTTP typically serves packages. If you want to use HTTP, then set up and configure a web server such as Apache 2, `lighttpd`, or Python web server on the machine serving the packages.

To keep things simple, this section describes how to set up a Python web server to share package feeds from the developer's machine. Although this server might not be the best for a production environment, the setup is simple and straight forward. Should you want to use a different server more suited for production (e.g. Apache 2, `Lighttpd`, or `Nginx`), take the appropriate steps to do so.

From within the *Build Directory* where you have built an image based on your packaging choice (i.e. the `PACKAGE_CLASSES` setting), simply start the server. The following example assumes a *Build Directory* of `bitbake-builds/build` and a `PACKAGE_CLASSES` setting of `"package_rpm"`:

```
$ cd bitbake-builds/build/tmp/deploy/rpm
$ python3 -m http.server
```

## Target Setup

Setting up the target differs depending on the package management system. This section provides information for RPM, IPK, and DEB.

## Using RPM

The *Dandified Packaging* (DNF) performs runtime package management of RPM packages. In order to use DNF for runtime package management, you must perform an initial setup on the target machine for cases where the `PACKAGE_FEED_*` variables were not set as part of the image that is running on the target. This means if you built your image and did not use these variables as part of the build and your image is now running on the target, you need to perform the steps in this section if you want to use runtime package management.

### Nota

For information on the `PACKAGE_FEED_*` variables, see `PACKAGE_FEED_ARCHS`, `PACKAGE_FEED_BASE_PATHS`, and `PACKAGE_FEED_URI` in the Yocto Project Reference Manual variables glossary.

On the target, you must inform DNF that package databases are available. You do this by creating a file named `/etc/yum.repos.d/oe-packages.repo` and defining the `oe-packages`.

As an example, assume the target is able to use the following package databases: `all`, `i586`, and `qemux86` from a server named `my.server`. The specifics for setting up the web server are up to you. The critical requirement is that the URIs in the target repository configuration point to the correct remote location for the feeds.

**i Nota**

For development purposes, you can point the web server to the build system's `deploy` directory. However, for production use, it is better to copy the package directories to a location outside of the build area and use that location. Doing so avoids situations where the build system overwrites or changes the `deploy` directory.

When telling DNF where to look for the package databases, you must declare individual locations per architecture or a single location used for all architectures. You cannot do both:

- *Create an Explicit List of Architectures:* Define individual base URLs to identify where each package database is located:

```
[oe-packages]
baseurl=http://my.server/rpm/i586 http://my.server/rpm/qemux86 http://my.
→server/rpm/all
```

This example informs DNF about individual package databases for all three architectures.

- *Create a Single (Full) Package Index:* Define a single base URL that identifies where a full package database is located:

```
[oe-packages]
baseurl=http://my.server/rpm
```

This example informs DNF about a single package database that contains all the package index information for all supported architectures.

Once you have informed DNF where to find the package databases, you need to fetch them:

```
# dnf makecache
```

DNF is now able to find, install, and upgrade packages from the specified repository or repositories.

**i Nota**

See the [DNF documentation](#) for additional information.

## Using IPK

The `opkg` application performs runtime package management of IPK packages. You must perform an initial setup for `opkg` on the target machine if the `PACKAGE_FEED_ARCHS`, `PACKAGE_FEED_BASE_PATHS`, and `PACKAGE_FEED_URIS` variables have not been set or the target image was built before the variables were set.

The `opkg` application uses configuration files to find available package databases. Thus, you need to create a configuration file inside the `/etc/opkg/` directory, which informs `opkg` of any repository you want to use.

As an example, suppose you are serving packages from a `ipk/` directory containing the `i586`, `all`, and `qemux86` databases through an HTTP server named `my.server`. On the target, create a configuration file (e.g. `my_repo.conf`) inside the `/etc/opkg/` directory containing the following:

```
src/gz all http://my.server/ipk/all
src/gz i586 http://my.server/ipk/i586
src/gz qemux86 http://my.server/ipk/qemux86
```

Next, instruct `opkg` to fetch the repository information:

```
# opkg update
```

The `opkg` application is now able to find, install, and upgrade packages from the specified repository.

## Using DEB

The `apt` application performs runtime package management of DEB packages. This application uses a source list file to find available package databases. You must perform an initial setup for `apt` on the target machine if the `PACKAGE_FEED_ARCHS`, `PACKAGE_FEED_BASE_PATHS`, and `PACKAGE_FEED_URIS` variables have not been set or the target image was built before the variables were set.

To inform `apt` of the repository you want to use, you might create a list file (e.g. `my_repo.list`) inside the `/etc/apt/sources.list.d/` directory. As an example, suppose you are serving packages from a `deb/` directory containing the `i586`, `all`, and `qemux86` databases through an HTTP server named `my.server`. The list file should contain:

```
deb http://my.server/deb/all ./
deb http://my.server/deb/i586 ./
deb http://my.server/deb/qemux86 ./
```

Next, instruct the `apt` application to fetch the repository information:

```
$ sudo apt update
```

After this step, `apt` is able to find, install, and upgrade packages from the specified repository.

## 8.29.5 Generating and Using Signed Packages

In order to add security to RPM packages used during a build, you can take steps to securely sign them. Once a signature is verified, the OpenEmbedded build system can use the package in the build. If security fails for a signed package, the build system stops the build.

This section describes how to sign RPM packages during a build and how to use signed package feeds (repositories) when doing a build.

## Signing RPM Packages

To enable signing RPM packages, you must modify the `rpm` recipe configuration to include support for OpenPGP signing. That may be done either in a `.bbappend` for the `rpm` recipe:

```
PACKAGECONFIG:append = " sequoia"
```

or in a *Configuration File*:

```
PACKAGECONFIG:append:pn-rpm-native = " sequoia"
PACKAGECONFIG:append:pn-rpm = " sequoia"
```

You must also set up the following settings in a *Configuration File*:

```
# Inherit sign_rpm.bbclass to enable signing functionality
INHERIT += " sign_rpm"
# Define the GPG key that will be used for signing.
RPM_GPG_NAME = "key_name"
# Provide passphrase for the key
RPM_GPG_PASSPHRASE = "passphrase"
```

### Nota

Be sure to supply appropriate values for both *key\_name* and *passphrase*.

Aside from the `RPM_GPG_NAME` and `RPM_GPG_PASSPHRASE` variables in the previous example, two optional variables related to signing are available:

- *GPG\_BIN*: Specifies a `gpg` binary/wrapper that is executed when the package is signed.
- *GPG\_PATH*: Specifies the `gpg` home directory used when the package is signed.

## Processing Package Feeds

In addition to being able to sign RPM packages, you can also enable signed package feeds for IPK and RPM packages.

The steps you need to take to enable signed package feed use are similar to the steps used to sign RPM packages. You must define the following in your *build/conf/local.conf* or distro *configuration file*:

```
INHERIT += "sign_package_feed"
PACKAGE_FEED_GPG_NAME = "key_name"
PACKAGE_FEED_GPG_PASSPHRASE_FILE = "path_to_file_containing_passphrase"
```

For signed package feeds, the passphrase must be specified in a separate file, which is pointed to by the `PACKAGE_FEED_GPG_PASSPHRASE_FILE` variable. Regarding security, keeping a plain text passphrase out of the configuration is more secure.

Aside from the `PACKAGE_FEED_GPG_NAME` and `PACKAGE_FEED_GPG_PASSPHRASE_FILE` variables, three optional variables related to signed package feeds are available:



- `GPG_BIN` Specifies a `gpg` binary/wrapper that is executed when the package is signed.
- `GPG_PATH`: Specifies the `gpg` home directory used when the package is signed.
- `PACKAGE_FEED_GPG_SIGNATURE_TYPE`: Specifies the type of `gpg` signature. This variable applies only to RPM and IPK package feeds. Allowable values for the `PACKAGE_FEED_GPG_SIGNATURE_TYPE` are "ASC", which is the default and specifies ascii armored, and "BIN", which specifies binary.

### 8.29.6 Testing Packages With ptest

See the *Testing Packages With ptest* section of the Yocto Project Test Environment Manual.

### 8.29.7 Creating Node Package Manager (NPM) Packages

#### Avvertimento

The NPM fetcher is currently disabled due to security concerns. See [355cd22](#) for more information.

This section is left there if it is re-enabled in the future, but is currently obsolete.

NPM is a package manager for the JavaScript programming language. The Yocto Project supports the NPM [fetcher](#). You can use this fetcher in combination with `devtool` to create recipes that produce NPM packages.

There are two workflows that allow you to create NPM packages using `devtool`: the NPM registry modules method and the NPM project code method.

#### Nota

While it is possible to create NPM recipes manually, using `devtool` is far simpler.

Additionally, some requirements and caveats exist.

### Requirements and Caveats

You need to be aware of the following before using `devtool` to create NPM packages:

- Of the two methods that you can use `devtool` to create NPM packages, the registry approach is slightly simpler. However, you might consider the project approach because you do not have to publish your module in the [NPM registry](#), which is NPM's public registry.
- Be familiar with `devtool`.
- The NPM host tools need the native `nodejs-npm` package, which is part of the OpenEmbedded environment. You need to get the package by cloning the [meta-openembedded](#) repository. Be sure to add the path to your local copy to your `build/conf/bblayers.conf` file.
- `devtool` cannot detect native libraries in module dependencies. Consequently, you must manually add packages to your recipe.

- While deploying NPM packages, `devtool` cannot determine which dependent packages are missing on the target (e.g. the node runtime `nodejs`). Consequently, you need to find out what files are missing and be sure they are on the target.
- Although you might not need NPM to run your node package, it is useful to have NPM on your target. The NPM package name is `nodejs-npm`.

### Using the Registry Modules Method

This section presents an example that uses the `cute-files` module, which is a file browser web application.

#### Nota

You must know the `cute-files` module version.

The first thing you need to do is use `devtool` and the NPM fetcher to create the recipe:

```
$ devtool add "npm://registry.npmjs.org;package=cute-files;version=1.0.2"
```

The `devtool add` command runs `recipetool create` and uses the same fetch URI to download each dependency and capture license details where possible. The result is a generated recipe.

After running for quite a long time, in particular building the `nodejs-native` package, the command should end as follows:

```
INFO: Recipe /home/.../build/workspace/recipes/cute-files/cute-files_1.0.2.bb has
↳ been automatically created; further editing may be required to make it fully
↳ functional
```

The recipe file is fairly simple and contains every license that `recipetool` finds and includes the licenses in the recipe's `LIC_FILES_CHKSUM` variables. You need to examine the variables and look for those with "unknown" in the `LICENSE` field. You need to track down the license information for "unknown" modules and manually add the information to the recipe.

`recipetool` creates a "shrinkwrap" file for your recipe. Shrinkwrap files capture the version of all dependent modules. Many packages do not provide shrinkwrap files but `recipetool` will create a shrinkwrap file as it runs.

#### Nota

A package is created for each sub-module. This policy is the only practical way to have the licenses for all of the dependencies represented in the license manifest of the image.

The `devtool edit-recipe` command lets you take a look at the recipe:

```
$ devtool edit-recipe cute-files
# Recipe created by recipetool
# This is the basis of a recipe and may need further editing in order to be fully
↳ functional.
```

(continues on next page)

(continua dalla pagina precedente)

```

# (Feel free to remove these comments when editing.)

SUMMARY = "Turn any folder on your computer into a cute file browser, available on
↳the local network."

# WARNING: the following LICENSE and LIC_FILES_CHKSUM values are best guesses - it
↳is
# your responsibility to verify that the values are complete and correct.
#
# NOTE: multiple licenses have been detected; they have been separated with &
# in the LICENSE value for now since it is a reasonable assumption that all
# of the licenses apply. If instead there is a choice between the multiple
# licenses then you should change the value to separate the licenses with |
# instead of &. If there is any doubt, check the accompanying documentation
# to determine which situation is applicable.

SUMMARY = "Turn any folder on your computer into a cute file browser, available on
↳the local network."
LICENSE = "BSD-3-Clause & ISC & MIT"
LIC_FILES_CHKSUM = "file://LICENSE;md5=71d98c0a1db42956787b1909c74a86ca \
                    file://node_modules/accepts/LICENSE;
↳md5=bf1f9ad1e2e1d507aef4883fff7103de \
                    file://node_modules/array-flatten/LICENSE;
↳md5=44088ba57cb871a58add36ce51b8de08 \
...
                    file://node_modules/cookie-signature/Readme.md;
↳md5=57ae8b42de3dd0c1f22d5f4cf191e15a"

SRC_URI = " \
    npm://registry.npmjs.org/package=cute-files;version=${PV} \
    npmsh://${THISDIR}/${BPN}/npm-shrinkwrap.json \
    "

S = "${UNPACKDIR}/npm"

inherit npm

LICENSE:${PN} = "MIT"
LICENSE:${PN}-accepts = "MIT"
LICENSE:${PN}-array-flatten = "MIT"
...
LICENSE:${PN}-vary = "MIT"

```

Three key points in the previous example are:

- `SRC_URI` uses the NPM scheme so that the NPM fetcher is used.
- `recipetool` collects all the license information. If a sub-module's license is unavailable, the sub-module's name appears in the comments.
- The `inherit npm` statement causes the `npm` class to package up all the modules.

You can run the following command to build the `cute-files` package:

```
$ devtool build cute-files
```

Remember that `nodejs` must be installed on the target before your package.


Assuming 192.168.7.2 for the target's IP address, use the following command to deploy your package:

```
$ devtool deploy-target -s cute-files root@192.168.7.2
```

Once the package is installed on the target, you can test the application to show the contents of any directory:

```
$ cd /usr/lib/node_modules/cute-files
$ cute-files
```

On a browser, go to `http://192.168.7.2:3000` and you see the following:



You can find the recipe in `workspace/recipes/cute-files`. You can use the recipe in any layer you choose.

## Using the NPM Projects Code Method

Although it is useful to package modules already in the NPM registry, adding `node.js` projects under development is a more common developer use case.

This section covers the NPM projects code method, which is very similar to the "registry" approach described in the previous section. In the NPM projects method, you provide `devtool` with an URL that points to the source files.

Replicating the same example, (i.e. `cute-files`) use the following command:

```
$ devtool add https://github.com/martinaglv/cute-files.git
```

The recipe this command generates is very similar to the recipe created in the previous section. However, the `SRC_URI` looks like the following:

```
SRC_URI = " \
    git://github.com/martinaglv/cute-files.git;protocol=https;branch=master \
    npmsw://${THISDIR}/${BPN}/npm-shrinkwrap.json \
"
```

In this example, the main module is taken from the Git repository and dependencies are taken from the NPM registry. Other than those differences, the recipe is basically the same between the two methods. You can build and deploy the package exactly as described in the previous section that uses the registry modules method.

### 8.29.8 Adding custom metadata to packages

The variable `PACKAGE_ADD_METADATA` can be used to add additional metadata to packages. This is reflected in the package control/spec file. To take the ipk format for example, the `CONTROL` file stored inside would contain the additional metadata as additional lines.

The variable can be used in multiple ways, including using suffixes to set it for a specific package type and/or package. Note that the order of precedence is the same as this list:

- `PACKAGE_ADD_METADATA_<PKGTYPE>:<PN>`
- `PACKAGE_ADD_METADATA_<PKGTYPE>`
- `PACKAGE_ADD_METADATA:<PN>`
- `PACKAGE_ADD_METADATA`

`<PKGTYPE>` is a parameter and expected to be a distinct name of specific package type:

- IPK for `.ipk` packages
- DEB for `.deb` packages
- RPM for `.rpm` packages

`<PN>` is a parameter and expected to be a package name.

The variable can contain multiple [one-line] metadata fields separated by the literal sequence `'\n'`. The separator can be redefined using the variable flag `separator`.

Here is an example that adds two custom fields for ipk packages:

```
PACKAGE_ADD_METADATA_IPK = "Vendor: CustomIpk\nGroup:Applications/Spreadsheets"
```

## 8.30 Efficiently Fetching Source Files During a Build

The OpenEmbedded build system works with source files located through the `SRC_URI` variable. When you build something using BitBake, a big part of the operation is locating and downloading all of the source code. For images, downloading all the source for various packages can take a significant amount of time.

This section shows you how you can use mirrors to speed up fetching source files and how you can pre-fetch files all of which leads to more efficient use of resources and time.

### 8.30.1 Setting up Effective Mirrors

A good deal that goes into a Yocto Project build is simply downloading source code. Maybe you have been working with another build system for which you have built up a sizable directory of source tarballs. Or, perhaps someone else has such a directory for which you have read access. If so, you can save time by adding statements to your configuration file so that the build process checks local directories first for existing tarballs before checking the Internet.

Here is an efficient way to set it up in a *configuration file*:

```
SOURCE_MIRROR_URL ?= "file:///home/you/your-download-dir/"
INHERIT += "own-mirrors"
BB_GENERATE_MIRROR_TARBALLS = "1"
# BB_NO_NETWORK = "1"
```

In the previous example, the `BB_GENERATE_MIRROR_TARBALLS` variable causes the OpenEmbedded build system to generate tarballs of the Git repositories and store them in the `DL_DIR` directory. Due to performance reasons, generating and storing these tarballs is not the build system's default behavior.

You can also use the `PREMIRRORS` variable. For an example, see the variable's glossary entry in the Yocto Project Reference Manual.

### 8.30.2 Getting Source Files and Suppressing the Build

Another technique you can use to ready yourself for a successive string of build operations, is to pre-fetch all the source files without actually starting a build. This technique lets you work through any download issues and ultimately gathers all the source files into your download directory `build/downloads/`, which is located with `DL_DIR`.

Use the following BitBake command form to fetch all the necessary sources without starting the build:

```
$ bitbake target --runall=fetch
```

This variation of the BitBake command guarantees that you have all the sources for that BitBake target should you disconnect from the Internet and want to do the build later offline.

## 8.31 Selecting an Initialization Manager

By default, the *Poky* distro uses *SysVinit* as the initialization manager. There is also support for *BusyBox init*, a simpler implementation, as well as support for *systemd*, which is a full replacement for *init* with parallel starting of services, reduced shell overhead, increased security and resource limits for services, and other features that are used by many distributions.

Within the system, *SysVinit* and *BusyBox init* treat system components as services. These services are maintained as shell scripts stored in the `/etc/init.d/` directory.

*SysVinit* is more elaborate than *BusyBox init* and organizes services in different run levels. This organization is maintained by putting links to the services in the `/etc/rcN.d/` directories, where *N* is one of the following options: "S", "0", "1", "2", "3", "4", "5", or "6".

### Nota

Each runlevel has a dependency on the previous runlevel. This dependency allows the services to work properly.

Both *SysVinit* and *BusyBox init* are configured through the `/etc/inittab` file, with a very similar syntax, though of course *BusyBox init* features are more limited.

In comparison, *systemd* treats components as units. Using units is a broader concept as compared to using a service. A unit includes several different types of entities. *Service* is one of the types of entities. The runlevel concept in *SysVinit* corresponds to the concept of a target in *systemd*, where target is also a type of supported unit.

In systems with *SysVinit* or *BusyBox init*, services load sequentially (i.e. one by one) during init and parallelization is not supported. With *systemd*, services start in parallel. This method can have an impact on the startup performance of a given service, though *systemd* will also provide more services by default, therefore increasing the total system boot time. *systemd* also substantially increases system size because of its multiple components and the extra dependencies it pulls.

By contrast, *BusyBox init* is the simplest and the lightest solution and also comes with *BusyBox mdev* as device manager, a lighter replacement to *udev*, which *SysVinit* and *systemd* both use.

The "*Selecting a Device Manager*" chapter has more details about device managers.

### 8.31.1 Using SysVinit with udev

*SysVinit* with the *udev* device manager corresponds to the default setting in *Poky*. This corresponds to setting:

```
INIT_MANAGER = "sysvinit"
```

### 8.31.2 Using BusyBox init with BusyBox mdev

*BusyBox init* with *BusyBox mdev* is the simplest and lightest solution for small root filesystems. All you need is *BusyBox*, which most systems have anyway:

```
INIT_MANAGER = "mdev-busybox"
```

### 8.31.3 Using systemd

The last option is to use systemd together with the udev device manager. This is the most powerful and versatile solution, especially for more complex systems:

```
INIT_MANAGER = "systemd"
```

This will enable systemd and remove sysvinit components from the image. See [meta/conf/distro/include/init-manager-systemd.inc](#) for exact details on what this does.

#### Controlling systemd from the target command line

Here is a quick reference for controlling systemd from the command line on the target. Instead of opening and sometimes modifying files, most interaction happens through the `systemctl` and `journalctl` commands:

- `systemctl status`: show the status of all services
- `systemctl status <service>`: show the status of one service
- `systemctl [start|stop] <service>`: start or stop a service
- `systemctl [enable|disable] <service>`: enable or disable a service at boot time
- `systemctl list-units`: list all available units
- `journalctl -a`: show all logs for all services
- `journalctl -f`: show only the last log entries, and keep printing updates as they arrive
- `journalctl -u`: show only logs from a particular service

#### Using systemd-journald without a traditional syslog daemon

Counter-intuitively, `systemd-journald` is not a syslog runtime or provider, and the proper way to use `systemd-journald` as your sole logging mechanism is to effectively disable syslog entirely by setting these variables in your distribution configuration file:

```
VIRTUAL-RUNTIME_syslog = ""  
VIRTUAL-RUNTIME_base-utils-syslog = ""
```

Doing so will prevent `rsyslog` / `busybox-syslog` from being pulled in by default, leaving only `systemd-journald`.

#### Summary

The Yocto Project supports three different initialization managers, offering increasing levels of complexity and functionality:



|                                 | BusyBox init  | SysVinit          | systemd           |
|---------------------------------|---------------|-------------------|-------------------|
| Size                            | Small         | Small             | Big <sup>1</sup>  |
| Complexity                      | Small         | Medium            | High              |
| Support for boot profiles       | No            | Yes ("runlevels") | Yes ("targets")   |
| Services defined as             | Shell scripts | Shell scripts     | Description files |
| Starting services in parallel   | No            | No                | Yes               |
| Setting service resource limits | No            | No                | Yes               |
| Support service isolation       | No            | No                | Yes               |
| Integrated logging              | No            | No                | Yes               |

## 8.32 Selecting a Device Manager

The Yocto Project provides multiple ways to manage the device manager (`/dev`):

- **Persistent and Pre-Populated `/dev`:** For this case, the `/dev` directory is persistent and the required device nodes are created during the build.
- **Use `devtmpfs` with a Device Manager:** For this case, the `/dev` directory is provided by the kernel as an in-memory file system and is automatically populated by the kernel at runtime. Additional configuration of device nodes is done in user space by a device manager like `udev` or `busybox-mdev`.

### 8.32.1 Using Persistent and Pre-Populated `/dev`

To use the static method for device population, you need to set the `USE_DEVFS` variable to "0" as follows:

```
USE_DEVFS = "0"
```

The content of the resulting `/dev` directory is defined in a Device Table file. The `IMAGE_DEVICE_TABLES` variable defines the Device Table to use and should be set in the machine or distro *configuration file*. Alternatively, you can set this variable in your *build/conf/local.conf* configuration file.

If you do not define the `IMAGE_DEVICE_TABLES` variable, the default `device_table-minimal.txt` is used:

```
IMAGE_DEVICE_TABLES = "device_table-mymachine.txt"
```

The population is handled by the `makedevs` utility during image creation:

### 8.32.2 Using `devtmpfs` and a Device Manager

To use the dynamic method for device population, you need to use (or be sure to set) the `USE_DEVFS` variable to "1", which is the default:

```
USE_DEVFS = "1"
```

<sup>1</sup> Using `systemd` increases the `core-image-minimal` image size by 160% for `qemux86-64` on `Mickledore (4.2)`, compared to `SysVinit`.

With this setting, the resulting `/dev` directory is populated by the kernel using `devtmpfs`. Make sure the corresponding kernel configuration variable `CONFIG_DEVTMPFS` is set when building you build a Linux kernel.

All devices created by `devtmpfs` will be owned by `root` and have permissions `0600`.

To have more control over the device nodes, you can use a device manager like `udev` or `busybox-mdev`. You choose the device manager by defining the `VIRTUAL-RUNTIME_dev_manager` variable in your machine or distro *configuration file*. Alternatively, you can set this variable in your `build/conf/local.conf` configuration file:

```
VIRTUAL-RUNTIME_dev_manager = "udev"

# Some alternative values
# VIRTUAL-RUNTIME_dev_manager = "busybox-mdev"
# VIRTUAL-RUNTIME_dev_manager = "systemd"
```

## 8.33 Using an External SCM

If you're working on a recipe that pulls from an external Source Code Manager (SCM), it is possible to have the OpenEmbedded build system notice new recipe changes added to the SCM and then build the resulting packages that depend on the new recipes by using the latest versions. This only works for SCMs from which it is possible to get a sensible revision number for changes. Currently, you can do this with Apache Subversion (SVN) and Git.

To enable this behavior, the *PV* of the recipe needs to include a `+` sign in its assignment. Here is an example:

```
PV = "1.2.3+git"
```

*Bitbake* later includes the source control information in *PKGVS* during the packaging phase.

Then, you can add the following to your `build/conf/local.conf` file:

```
SRCREV:pn-PN = "${AUTOREV}"
```

*PN* is the name of the recipe for which you want to enable automatic source revision updating.

If you do not want to update your local configuration file, you can add the following directly to the recipe to finish enabling the feature:

```
SRCREV = "${AUTOREV}"
```

The Yocto Project provides a distribution named `poky-bleeding`, whose configuration file contains the line:

```
require conf/distro/include/poky-floating-revisions.inc
```

This line pulls in the listed include file that defines the set of `AUTOREV`-enabled recipes:

```
INHERIT += "poky-bleeding"

POKY_AUTOREV_RECIPES = "\
    libmatchbox \
```

(continues on next page)

(continua dalla pagina precedente)

```
opkg-utils \
matchbox-config-gtk \
matchbox-desktop \
matchbox-keyboard \
matchbox-panel-2 \
matchbox-terminal \
matchbox-theme-sato \
matchbox-wm \
pseudo \
puzzles \
sato-icon-theme \
sato-screenshot \
settings-daemon \
"
```

This allows you to experiment with building a distribution that tracks the latest development source for numerous packages.

**i Nota**

The `poky-bleeding` distribution is not tested on a regular basis. Keep this in mind if you use it.

## 8.34 Maintaining Build Output Quality with `buildhistory`

Many factors can influence the quality of a build. For example, if you upgrade a recipe to use a new version of an upstream software package or you experiment with some new configuration options, subtle changes can occur that you might not detect until later. Consider the case where your recipe is using a newer version of an upstream package. In this case, a new version of a piece of software might introduce an optional dependency on another library, which is auto-detected. If that library has already been built when the software is building, the software will link to the built library and that library will be pulled into your image along with the new software even if you did not want the library.

The `buildhistory` class helps you maintain the quality of your build output. You can use the class to highlight unexpected and possibly unwanted changes in the build output. When you enable build history, it records information about the contents of each package and image and then commits that information to a local Git repository where you can examine the information.

The remainder of this section describes the following:

- *How you can enable and disable build history*
- *How to understand what the build history contains*
- *How to limit the information used for build history*
- *How to examine the build history from both a command-line and web interface*

### 8.34.1 Enabling and Disabling Build History

Build history is disabled by default. To enable it, add the following *INHERIT* statement and set the *BUILDHISTORY\_COMMIT* variable to "1" in a *configuration file*, such as the *build/conf/local.conf* file:

```
INHERIT += "buildhistory"
BUILDHISTORY_COMMIT = "1"
```

Enabling build history as previously described causes the OpenEmbedded build system to collect build output information and commit it as a single commit to a local *Git* repository.


#### **Nota**

Enabling build history increases your build times slightly, particularly for images, and increases the amount of disk space used during the build.

You can disable build history by removing the previous statements from your *configuration file*.

### 8.34.2 Understanding What the Build History Contains

Build history information is kept in `${TOPDIR}/buildhistory` in the *Build Directory* as defined by the *BUILDHISTORY\_DIR* variable. Here is an example abbreviated listing:



At the top level, there is a `metadata-revs` file that lists the revisions of the repositories for the enabled layers when the build was produced. The rest of the data splits into separate `packages`, `images` and `sdk` directories, the contents of which are described as follows.

### Build History Package Information

The history for each package contains a text file that has name-value pairs with information about the package. For example, `buildhistory/packages/i586-poky-linux/busybox/busybox/latest` contains the following:

```
PV = 1.22.1
PR = r32
RPROVIDES =
RDEPENDS = glibc (>= 2.20) update-alternatives-opkg
RRECOMMENDS = busybox-syslog busybox-udhcpd update-rc.d
PKGSIZE = 540168
FILES = /usr/bin/* /usr/sbin/* /usr/lib/busybox/* /usr/lib/lib*.so.* \
        /etc /com /var /bin/* /sbin/* /lib/*.so.* /lib/udev/rules.d \
        /usr/lib/udev/rules.d /usr/share/busybox /usr/lib/busybox/* \
        /usr/share/pixmaps /usr/share/applications /usr/share/idl \
        /usr/share/omf /usr/share/sounds /usr/lib/bonobo/servers
FILELIST = /bin/busybox /bin/busybox.nosuid /bin/busybox.suid /bin/sh \
        /etc/busybox.links.nosuid /etc/busybox.links.suid
```

Most of these name-value pairs correspond to variables used to produce the package. The exceptions are `FILELIST`, which is the actual list of files in the package, and `PKGSIZE`, which is the total size of files in the package in bytes.

There is also a file that corresponds to the recipe from which the package came (e.g. `buildhistory/packages/i586-poky-linux/busybox/latest`):

```
PV = 1.22.1
PR = r32
DEPENDS = initscripts kern-tools-native update-rc.d-native \
        virtual/i586-poky-linux-compilerlibs virtual/i586-poky-linux-gcc \
        virtual/libc virtual/update-alternatives
PACKAGES = busybox-ptest busybox-httpd busybox-udhcpd busybox-udhcp \
        busybox-syslog busybox-mdev busybox-hwclock busybox-dbg \
        busybox-staticdev busybox-dev busybox-doc busybox-locale busybox
```

Finally, for those recipes fetched from a version control system (e.g., Git), there is a file that lists source revisions that are specified in the recipe and the actual revisions used during the build. Listed and actual revisions might differ when `SRCREV` is set to `${AUTOREV}`. Here is an example assuming `buildhistory/packages/qemux86-poky-linux/linux-yocto/latest_srcrev`:

```
# SRCREV_machine = "38cd560d5022ed2dbd1ab0dca9642e47c98a0aa1"
SRCREV_machine = "38cd560d5022ed2dbd1ab0dca9642e47c98a0aa1"
# SRCREV_meta = "a227f20eff056e511d504b2e490f3774ab260d6f"
SRCREV_meta = "a227f20eff056e511d504b2e490f3774ab260d6f"
```

You can use the `buildhistory-collect-srcrevs` command with the `-a` option to collect the stored *SRCREV* values from build history and report them in a format suitable for use in global configuration (e.g., a distro include *configuration file*) to override floating *AUTOREV* values to a fixed set of revisions. Here is some example output from this command:

```
$ buildhistory-collect-srcrevs -a
# all-poky-linux
SRCREV:pn-ca-certificates = "07de54fdcc5806bde549e1edf60738c6bccf50e8"
SRCREV:pn-update-rc.d = "8636cf478d426b568c1be11dbd9346f67e03adac"
# core2-64-poky-linux
SRCREV:pn-binutils = "87d4632d36323091e731eb07b8aa65f90293da66"
SRCREV:pn-btrfs-tools = "8ad326b2f28c044cb6ed9016d7c3285e23b673c8"
SRCREV_bzip2-tests:pn-bzip2 = "f9061c030a25de5b6829e1abf373057309c734c0"
SRCREV:pn-e2fsprogs = "02540dedd3ddc52c6ae8aaa8a95ce75c3f8be1c0"
SRCREV:pn-file = "504206e53a89fd6eed71aeaf878aa3512418eab1"
SRCREV_glibc:pn-glibc = "24962427071fa532c3c48c918e9d64d719cc8a6c"
SRCREV:pn-gnome-desktop-testing = "e346cd4ed2e2102c9b195b614f3c642d23f5f6e7"
SRCREV:pn-init-system-helpers = "dbd9197569c0935029acd5c9b02b84c68fd937ee"
SRCREV:pn-kmod = "b6ecfc916a17eab8f93be5b09f4e4f845aab3d1"
SRCREV:pn-libnsl2 = "82245c0c58add79a8e34ab0917358217a70e5100"
SRCREV:pn-libseccomp = "57357d2741a3b3d3e8425889a6b79a130e0fa2f3"
SRCREV:pn-libxcrypt = "50cf2b6dd4fdf04309445f2eec8de7051d953abf"
SRCREV:pn-ncurses = "51d0fd9cc3edb975f04224f29f777f8f448e8ced"
SRCREV:pn-procps = "19a508ea121c0c4ac6d0224575a036de745eaa8"
SRCREV:pn-psmisc = "5fab6b7ab385080f1db725d6803136ec1841a15f"
SRCREV:pn-ptest-runner = "bcb82804daa8f725b6add259dcef2067e61a75aa"
SRCREV:pn-shared-mime-info = "18e558fa1c8b90b86757ade09a4ba4d6a6cf8f70"
SRCREV:pn-zstd = "e47e674cd09583ff0503f0f6defd6d23d8b718d3"
# qemux86_64-poky-linux
SRCREV_machine:pn-linux-yocto = "20301aeb1a64164b72bc72af58802b315e025c9c"
SRCREV_meta:pn-linux-yocto = "2d38a472b21ae343707c8bd64ac68a9eaca066a0"
# x86_64-linux
SRCREV:pn-binutils-cross-x86_64 = "87d4632d36323091e731eb07b8aa65f90293da66"
SRCREV_glibc:pn-cross-localedef-native = "24962427071fa532c3c48c918e9d64d719cc8a6c"
SRCREV_localedef:pn-cross-localedef-native =
→ "794da69788cbf9bf57b59a852f9f11307663fa87"
SRCREV:pn-debianutils-native = "de14223e5bffe15e374a441302c528ffc1cbcd57"
SRCREV:pn-libmodulemd-native = "ee80309bc766d781a144e6879419b29f444d94eb"
SRCREV:pn-virglrenderer-native = "363915595e05fb252e70d6514be2f0c0b5ca312b"
SRCREV:pn-zstd-native = "e47e674cd09583ff0503f0f6defd6d23d8b718d3"
```

#### Nota

Here are some notes on using the `buildhistory-collect-srcrevs` command:

- By default, only values where the *SRCREV* was not hardcoded (usually when *AUTOREV* is used) are reported. Use the `-a` option to see all *SRCREV* values.
- The output statements might not have any effect if overrides are applied elsewhere in the build system configuration. Use the `-f` option to add the `forcevariable` override to each output line if you need to work around this restriction.
- The script does apply special handling when building for multiple machines. However, the script does place a comment before each set of values that specifies which triplet to which they belong as previously shown (e.g., `i586-poky-linux`).

## Build History Image Information

The files produced for each image are as follows:

- `image-files`: A directory containing selected files from the root filesystem. The files are defined by *BUILDHISTORY\_IMAGE\_FILES*.
- `build-id.txt`: Human-readable information about the build configuration and metadata source revisions. This file contains the full build header as printed by BitBake.
- `*.dot`: Dependency graphs for the image that are compatible with `graphviz`.
- `files-in-image.txt`: A list of files in the image with permissions, owner, group, size, and symlink information.
- `image-info.txt`: A text file containing name-value pairs with information about the image. See the following listing example for more information.
- `installed-package-names.txt`: A list of installed packages by name only.
- `installed-package-sizes.txt`: A list of installed packages ordered by size.
- `installed-packages.txt`: A list of installed packages with full package filenames.

### Nota

Installed package information is able to be gathered and produced even if package management is disabled for the final image.

Here is an example of `image-info.txt`:

```
DISTRO = poky
DISTRO_VERSION = 3.4+snapshot-a0245d7be08f3d24ea1875e9f8872aa6bbff93be
USER_CLASSES = buildstats
IMAGE_CLASSES = qemuboot qemuboot license_image
IMAGE_FEATURES = allow-empty-password empty-root-password allow-root-login post-
↳install-logging
IMAGE_LINGUAS =
IMAGE_INSTALL = packagegroup-core-boot speex speexdsp
```

(continues on next page)

(continua dalla pagina precedente)

```

BAD_RECOMMENDATIONS =
NO_RECOMMENDATIONS =
PACKAGE_EXCLUDE =
ROOTFS_POSTPROCESS_COMMAND = ssh_allow_empty_password ssh_allow_root_login ↵
↵postinst_enable_logging rootfs_update_timestamp write_image_test_data empty_
↵var_volatile sort_passwd rootfs_reproducible
IMAGE_POSTPROCESS_COMMAND = buildhistory_get_imageinfo
IMAGESIZE = 9265

```

Other than `IMAGESIZE`, which is the total size of the files in the image in Kbytes, the name-value pairs are variables that may have influenced the content of the image. This information is often useful when you are trying to determine why a change in the package or file listings has occurred.

### Using Build History to Gather Image Information Only

As you can see, build history produces image information, including dependency graphs, so you can see why something was pulled into the image. If you are just interested in this information and not interested in collecting specific package or SDK information, you can enable writing only image information without any history by adding the following to a *configuration file*:

```

INHERIT += "buildhistory"
BUILDHISTORY_COMMIT = "0"
BUILDHISTORY_FEATURES = "image"

```

Here, you set the `BUILDHISTORY_FEATURES` variable to use the image feature only.

### Build History SDK Information

Build history collects similar information on the contents of SDKs (e.g. `bitbake -c populate_sdk imagename`) as compared to information it collects for images. Furthermore, this information differs depending on whether an extensible or standard SDK is being produced.

The following list shows the files produced for SDKs:

- `files-in-sdk.txt`: A list of files in the SDK with permissions, owner, group, size, and symlink information. This list includes both the host and target parts of the SDK.
- `sdk-info.txt`: A text file containing name-value pairs with information about the SDK. See the following listing example for more information.
- `sstate-task-sizes.txt`: A text file containing name-value pairs with information about task group sizes (e.g. *do\_populate\_sysroot* tasks have a total size). The `sstate-task-sizes.txt` file exists only when an extensible SDK is created.
- `sstate-package-sizes.txt`: A text file containing name-value pairs with information for the shared-state packages and sizes in the SDK. The `sstate-package-sizes.txt` file exists only when an extensible SDK is created.



- `sdk-files`: A folder that contains copies of the files mentioned in `BUILDHISTORY_SDK_FILES` if the files are present in the output. Additionally, the default value of `BUILDHISTORY_SDK_FILES` is specific to the extensible SDK although you can set it differently if you would like to pull in specific files from the standard SDK.

The default files are `build/conf/local.conf`, `build/conf/bblayers.conf`, `build/conf/auto.conf`, `conf/locked-signs.inc`, and `conf/devtool.conf`. Thus, for an extensible SDK, these files get copied into the `sdk-files` directory.

- The following information appears under each of the `host` and `target` directories for the portions of the SDK that run on the host and on the target, respectively:

#### Nota

The following files for the most part are empty when producing an extensible SDK because this type of SDK is not constructed from packages as is the standard SDK.

- `depends.dot`: Dependency graph for the SDK that is compatible with `graphviz`.
- `installed-package-names.txt`: A list of installed packages by name only.
- `installed-package-sizes.txt`: A list of installed packages ordered by size.
- `installed-packages.txt`: A list of installed packages with full package filenames.

Here is an example of `sdk-info.txt`:

```
DISTRO = poky
DISTRO_VERSION = 1.3+snapshot-20130327
SDK_NAME = poky-glibc-i686-arm
SDK_VERSION = 1.3+snapshot
SDKMACHINE =
SDKIMAGE_FEATURES = dev-pkgs dbg-pkgs
BAD_RECOMMENDATIONS =
SDKSIZE = 352712
```

Other than `SDKSIZE`, which is the total size of the files in the SDK in Kbytes, the name-value pairs are variables that might have influenced the content of the SDK. This information is often useful when you are trying to determine why a change in the package or file listings has occurred.

## Examining Build History Information

You can examine build history output from the command line or from a web interface.

To see any changes that have occurred (assuming you have `BUILDHISTORY_COMMIT = "1"`), you can simply use any Git command that allows you to view the history of a repository. Here is one method:

```
$ git log -p
```

You need to realize, however, that this method does show changes that are not significant (e.g. a package's size changing by a few bytes).

There is a command-line tool called `buildhistory-diff`, though, that queries the Git repository and prints just the differences that might be significant in human-readable form. Here is an example:

```
$ bitbake-builds/layers/openembedded-core/scripts/buildhistory-diff . HEAD^
Changes to images/qemux86_64/glibc/core-image-minimal (files-in-image.txt):
    /etc/anotherpkg.conf was added
    /sbin/anotherpkg was added
    * (installed-package-names.txt):
    *   anotherpkg was added
Changes to images/qemux86_64/glibc/core-image-minimal (installed-package-names.
↪txt):
    anotherpkg was added
packages/qemux86_64-poky-linux/v86d: PACKAGES: added "v86d-extras"
    * PR changed from "r0" to "r1"
    * PV changed from "0.1.10" to "0.1.12"
packages/qemux86_64-poky-linux/v86d/v86d: PKGSIZE changed from 110579 to 144381↪
↪(+30%)
    * PR changed from "r0" to "r1"
    * PV changed from "0.1.10" to "0.1.12"
```

#### **Nota**


The `buildhistory-diff` tool requires the `GitPython` package. Be sure to install it using `Pip3` as follows:

```
$ pip3 install GitPython --user
```

Alternatively, you can install `python3-git` using the appropriate distribution package manager (e.g. `apt`, `dnf`, or `zipper`).

To see changes to the build history using a web interface, follow the instruction in the `README` file [here](#).

Here is a sample screenshot of the interface:



## 8.35 Debugging Tools and Techniques

The exact method for debugging build failures depends on the nature of the problem and on the system's area from which the bug originates. Standard debugging practices such as comparison against the last known working version with examination of the changes and the re-application of steps to identify the one causing the problem are valid for the Yocto Project just as they are for any other system. Even though it is impossible to detail every possible potential failure, this section provides some general tips to aid in debugging given a variety of situations.

### **i** Nota

A useful feature for debugging is the error reporting tool. Configuring the Yocto Project to use this tool causes the OpenEmbedded build system to produce error reporting commands as part of the console output. You can enter the commands after the build completes to log error information into a common database, that can help you figure out what might be going wrong. For information on how to enable and use this feature, see the "[Using the Error Reporting Tool](#)" section.

The following list shows the debugging topics in the remainder of this section:

- "[Viewing Logs from Failed Tasks](#)" describes how to find and view logs from tasks that failed during the build process.
- "[Viewing Variable Values](#)" describes how to use the BitBake `-e` option to examine variable values after a recipe has been parsed.

- "*Viewing Package Information with oe-pkgdata-util*" describes how to use the `oe-pkgdata-util` utility to query `PKGDATA_DIR` and display package-related information for built packages.
- "*Viewing Dependencies Between Recipes and Tasks*" describes how to use the BitBake `-g` option to display recipe dependency information used during the build.
- "*Viewing Task Variable Dependencies*" describes how to use the `bitbake-dumpsig` command in conjunction with key subdirectories in the *Build Directory* to determine variable dependencies.
- "*Running Specific Tasks*" describes how to use several BitBake options (e.g. `-c`, `-C`, and `-f`) to run specific tasks in the build chain. It can be useful to run tasks "out-of-order" when trying isolate build issues.
- "*General BitBake Problems*" describes how to use BitBake's `-D` debug output option to reveal more about what BitBake is doing during the build.
- "*Building with No Dependencies*" describes how to use the BitBake `-b` option to build a recipe while ignoring dependencies.
- "*Recipe Logging Mechanisms*" describes how to use the many recipe logging functions to produce debugging output and report errors and warnings.
- "*Debugging Parallel Make Races*" describes how to debug situations where the build consists of several parts that are run simultaneously and when the output or result of one part is not ready for use with a different part of the build that depends on that output.
- "*Debugging With the GNU Project Debugger (GDB) Remotely*" describes how to use GDB to allow you to examine running programs, which can help you fix problems.
- "*Debugging with the GNU Project Debugger (GDB) on the Target*" describes how to use GDB directly on target hardware for debugging.
- "*Other Debugging Tips*" describes miscellaneous debugging tips that can be useful.

### 8.35.1 Viewing Logs from Failed Tasks

You can find the log for a task in the file `${WORKDIR}/temp/log.do_taskname`. For example, the log for the *do\_compile* task of the QEMU minimal image for the x86 machine (`qemux86`) might be in `tmp/work/qemux86-poky-linux/core-image-minimal/1.0-r0/temp/log.do_compile`. To see the commands *BitBake* ran to generate a log, look at the corresponding `run.do_taskname` file in the same directory.

`log.do_taskname` and `run.do_taskname` are actually symbolic links to `log.do_taskname.pid` and `log.run_taskname.pid`, where *pid* is the PID the task had when it ran. The symlinks always point to the files corresponding to the most recent run.

### 8.35.2 Viewing Variable Values

Sometimes you need to know the value of a variable as a result of BitBake's parsing step. This could be because some unexpected behavior occurred in your project. Perhaps an attempt to *modify a variable* did not work out as expected.

BitBake's `bitbake-getvar` command is used to display variable values after parsing. The following command displays the variable value for *OVERRIDES* after the configuration files (i.e. `local.conf`, *build/conf/bblayers.conf*, `bitbake.conf` and so forth) have been parsed:

```
$ bitbake-getvar OVERRIDES
```

The following command displays the value of *PV* after a specific recipe has been parsed:

```
$ bitbake-getvar -r recipename PV
```

### Nota

Each recipe has its own private set of variables (datastore). Internally, after parsing the configuration, a copy of the resulting datastore is made prior to parsing each recipe. This copying implies that variables set in one recipe will not be visible to other recipes.

Likewise, each task within a recipe gets a private datastore based on the recipe datastore, which means that variables set within one task will not be visible to other tasks.

In the output of `bitbake-getvar`, the line containing the value of the variable is preceded by a description of how the variable got its value, including temporary values that were later overridden. This description also includes variable flags (varflags) set on the variable. The output can be very helpful during debugging.

Variables that are exported to the environment are preceded by `export` in the output of `bitbake-getvar`. See the following example:

```
export CC="i586-poky-linux-gcc -m32 -march=i586 --sysroot=/home/ulf/poky/build/tmp/
↪sysroots/qemux86"
```

Shell functions and tasks can also be inspected with the same mechanism:

```
$ bitbake-getvar -r recipename do_install
```

For Python functions and tasks, `bitbake -e recipename` can be used instead.

Moreover, the output of the `bitbake -e` and `bitbake -e recipe` commands includes the following information:

- The output starts with a tree listing all configuration files and classes included globally, recursively listing the files they include or inherit in turn. Much of the behavior of the OpenEmbedded build system (including the behavior of the *Normal Recipe Build Tasks*) is implemented in the *base* class and the classes it inherits, rather than being built into BitBake itself.
- After the variable values, all functions appear in the output. For shell functions, variables referenced within the function body are expanded. If a function has been modified using overrides or using override-style operators like `:append` and `:prepend`, then the final assembled function body appears in the output.

### 8.35.3 Viewing Package Information with `oe-pkgdata-util`

You can use the `oe-pkgdata-util` command-line utility to query *PKGDATA\_DIR* and display various package-related information. When you use the utility, you must use it to view information on packages that have already been built.

Here are a few of the available `oe-pkgdata-util` subcommands.

**i Nota**

You can use the standard `*` and `?` globbing wildcards as part of package names and paths.

- `oe-pkgdata-util list-pkgs [pattern]`: Lists all packages that have been built, optionally limiting the match to packages that match `pattern`.
- `oe-pkgdata-util list-pkg-files package ...`: Lists the files and directories contained in the given packages.

**i Nota**

A different way to view the contents of a package is to look at the `${WORKDIR}/packages-split` directory of the recipe that generates the package. This directory is created by the `do_package` task and has one subdirectory for each package the recipe generates, which contains the files stored in that package.

If you want to inspect the `${WORKDIR}/packages-split` directory, make sure that `rm_work` is not enabled when you build the recipe.

- `oe-pkgdata-util find-path path ...`: Lists the names of the packages that contain the given paths. For example, the following tells us that `/usr/share/man/man1/make.1` is contained in the `make-doc` package:

```
$ oe-pkgdata-util find-path /usr/share/man/man1/make.1
make-doc: /usr/share/man/man1/make.1
```

- `oe-pkgdata-util lookup-recipe package ...`: Lists the name of the recipes that produce the given packages.

For more information on the `oe-pkgdata-util` command, use the help facility:

```
$ oe-pkgdata-util --help
$ oe-pkgdata-util subcommand --help
```

## 8.35.4 Viewing Dependencies Between Recipes and Tasks

Sometimes it can be hard to see why BitBake wants to build other recipes before the one you have specified. Dependency information can help you understand why a recipe is built.

To generate dependency information for a recipe, run the following command:

```
$ bitbake -g recipename
```

This command writes the following files in the current directory:

- `pn-buildlist`: A list of recipes/targets involved in building *recipename*. "Involved" here means that at least one task from the recipe needs to run when building *recipename* from scratch. Targets that are in *ASSUME\_PROVIDED* are not listed.

- `task-depends.dot`: A graph showing dependencies between tasks.

The graphs are in DOT format and can be converted to images (e.g. using the `dot` tool from Graphviz).

#### Nota

- DOT files use a plain text format. The graphs generated using the `bitbake -g` command are often so large as to be difficult to read without special pruning (e.g. with BitBake's `-I` option) and processing. Despite the form and size of the graphs, the corresponding `.dot` files can still be possible to read and provide useful information.

As an example, the `task-depends.dot` file contains lines such as the following:

```
"libxslt.do_configure" -> "libxml2.do_populate_sysroot"
```

The above example line reveals that the `do_configure` task in `libxslt` depends on the `do_populate_sysroot` task in `libxml2`, which is a normal *DEPENDS* dependency between the two recipes.

- For an example of how `.dot` files can be processed, see the `scripts/contrib/graph-tool` Python script, which finds and displays paths between graph nodes.

You can use a different method to view dependency information by using either:

```
$ bitbake -g -u taskexp recipeName
```

or:

```
$ bitbake -g -u taskexp_ncurses recipeName
```

The `-u taskdep` option GUI window from which you can view build-time and runtime dependencies for the recipes involved in building `recipeName`. The `-u taskexp_ncurses` option uses `ncurses` instead of `GTK` to render the UI.

### 8.35.5 Viewing Task Variable Dependencies

As mentioned in the "Checksums (Signatures)" section of the BitBake User Manual, BitBake tries to automatically determine what variables a task depends on so that it can rerun the task if any values of the variables change. This determination is usually reliable. However, if you do things like construct variable names at runtime, then you might have to manually declare dependencies on those variables using `vardeps` as described in the "Variable Flags" section of the BitBake User Manual.

If you are unsure whether a variable dependency is being picked up automatically for a given task, you can list the variable dependencies BitBake has determined by doing the following:

1. Build the recipe containing the task:

```
$ bitbake recipeName
```

2. Inside the `STAMPS_DIR` directory, find the signature data (`sigdata`) file that corresponds to the task. The `sigdata` files contain a pickled Python database of all the metadata that went into creating the input checksum for the task. As an example, for the `do_fetch` task of the `db` recipe, the `sigdata` file might be found in the following location:

```
${BUILDDIR}/tmp/stamps/i586-poky-linux/db/6.0.30-r1.do_fetch.sigdata.  
→7c048c18222b16ff0bcee2000ef648b1
```

For tasks that are accelerated through the shared state (*sstate*) cache, an additional `siginfo` file is written into *SSTATE\_DIR* along with the cached task output. The `siginfo` files contain exactly the same information as `sigdata` files.

3. Run `bitbake-dumpsig` on the `sigdata` or `siginfo` file. Here is an example:

```
$ bitbake-dumpsig ${BUILDDIR}/tmp/stamps/i586-poky-linux/db/6.0.30-r1.do_fetch.  
→sigdata.7c048c18222b16ff0bcee2000ef648b1
```

In the output of the above command, you will find a line like the following, which lists all the (inferred) variable dependencies for the task. This list also includes indirect dependencies from variables depending on other variables, recursively:

```
Task dependencies: ['PV', 'SRCREV', 'SRC_URI', 'SRC_URI[sha256sum]', 'base_do_  
→fetch']
```

#### Nota

Functions (e.g. `base_do_fetch`) also count as variable dependencies. These functions in turn depend on the variables they reference.

The output of `bitbake-dumpsig` also includes the value each variable had, a list of dependencies for each variable, and *BB\_BASEHASH\_IGNORE\_VARS* information.

## 8.35.6 Debugging signature construction and unexpected task executions

There is a `bitbake-diffsigs` command for comparing two `siginfo` or `sigdata` files. This command can be helpful when trying to figure out what changed between two versions of a task. If you call `bitbake-diffsigs` with just one file, the command behaves like `bitbake-dumpsig`.

You can also use BitBake to dump out the signature construction information without executing tasks by using either of the following BitBake command-line options:

```
--dump-signatures=SIGNATURE_HANDLER  
-S SIGNATURE_HANDLER
```

#### Nota

Two common values for *SIGNATURE\_HANDLER* are "none" and "printdiff", which dump only the signature or compare the dumped signature with the most recent one, respectively. "printdiff" will try to establish the most recent signature match (e.g. in the *sstate* cache) and then compare the matched signatures to determine the stamps and delta where these two stamp trees diverge. This can be used to determine why tasks need to be re-run in situations where that is not expected.



Using BitBake with either of these options causes BitBake to dump out `sigdata` files in the `stamps` directory for every task it would have executed instead of building the specified target package.

### 8.35.7 Viewing Metadata Used to Create the Input Signature of a Shared State Task

Seeing what metadata went into creating the input signature of a shared state (`sstate`) task can be a useful debugging aid. This information is available in signature information (`siginfo`) files in `SSTATE_DIR`. For information on how to view and interpret information in `siginfo` files, see the "[Viewing Task Variable Dependencies](#)" section.

For conceptual information on shared state, see the "[Shared State](#)" section in the Yocto Project Overview and Concepts Manual.

### 8.35.8 Invalidating Shared State to Force a Task to Run

The OpenEmbedded build system uses [checksums](#) and [Shared State](#) cache to avoid unnecessarily rebuilding tasks. Collectively, this scheme is known as "shared state code".

As with all schemes, this one has some drawbacks. It is possible that you could make implicit changes to your code that the checksum calculations do not take into account. These implicit changes affect a task's output but do not trigger the shared state code into rebuilding a recipe. Consider an example during which a tool changes its output. Assume that the output of `rpmdeps` changes. The result of the change should be that all the `package` and `package_write_rpm` shared state cache items become invalid. However, because the change to the output is external to the code and therefore implicit, the associated shared state cache items do not become invalidated. In this case, the build process uses the cached items rather than running the task again. Obviously, these types of implicit changes can cause problems.

To avoid these problems during the build, you need to understand the effects of any changes you make. Realize that changes you make directly to a function are automatically factored into the checksum calculation. Thus, these explicit changes invalidate the associated area of shared state cache. However, you need to be aware of any implicit changes that are not obvious changes to the code and could affect the output of a given task.

When you identify an implicit change, you can easily take steps to invalidate the cache and force the tasks to run. The steps you can take are as simple as changing a function's comments in the source code. For example, to invalidate package shared state files, change the comment statements of `do_package` or the comments of one of the functions it calls. Even though the change is purely cosmetic, it causes the checksum to be recalculated and forces the build system to run the task again.

#### Nota

For an example of a commit that makes a cosmetic change to invalidate shared state, see this [commit](#).

### 8.35.9 Running Specific Tasks

Any given recipe consists of a set of tasks. The standard BitBake behavior in most cases is: `do_fetch`, `do_unpack`, `do_patch`, `do_configure`, `do_compile`, `do_install`, `do_package`, `do_package_write_*`, and `do_build`. The default task is `do_build` and any tasks on which it depends build first. Some tasks, such as `do_devshell`, are not part of the default

build chain. If you wish to run a task that is not part of the default build chain, you can use the `-c` option in BitBake. Here is an example:

```
$ bitbake matchbox-desktop -c devshell
```

The `-c` option respects task dependencies, which means that all other tasks (including tasks from other recipes) that the specified task depends on will be run before the task. Even when you manually specify a task to run with `-c`, BitBake will only run the task if it considers it "out of date". See the "*File Stamp e Riesecuzione dei Task*" section in the Yocto Project Overview and Concepts Manual for how BitBake determines whether a task is "out of date".

If you want to force an up-to-date task to be rerun (e.g. because you made manual modifications to the recipe's *WORKDIR* that you want to try out), then you can use the `-f` option.

#### Nota

The reason `-f` is never required when running the *do\_devshell* task is because the `[nostamp]` variable flag is already set for the task.

The following example shows one way you can use the `-f` option:

```
$ bitbake matchbox-desktop
    .
    .
make some changes to the source code in the work directory
    .
    .
$ bitbake matchbox-desktop -c compile -f
$ bitbake matchbox-desktop
```

This sequence first builds and then recompiles *matchbox-desktop*. The last command reruns all tasks (basically the packaging tasks) after the compile. BitBake recognizes that the *do\_compile* task was rerun and therefore understands that the other tasks also need to be run again.

Another, shorter way to rerun a task and all *Normal Recipe Build Tasks* that depend on it is to use the `-C` option.

#### Nota

This option is upper-cased and is separate from the `-c` option, which is lower-cased.

Using this option invalidates the given task and then runs the *do\_build* task, which is the default task if no task is given, and the tasks on which it depends. You could replace the final two commands in the previous example with the following single command:

```
$ bitbake matchbox-desktop -C compile
```

Internally, the `-f` and `-C` options work by tainting (modifying) the input checksum of the specified task. This tainting indirectly causes the task and its dependent tasks to be rerun through the normal task dependency mechanisms.

**i Nota**

BitBake explicitly keeps track of which tasks have been tainted in this fashion, and will print warnings such as the following for builds involving such tasks:

```
WARNING: /home/ulf/openembedded-core/meta/recipes-sato/matchbox-desktop/matchbox-  
→desktop_2.1.bb.do_compile is tainted from a forced run
```

The purpose of the warning is to let you know that the work directory and build output might not be in the clean state they would be in for a "normal" build, depending on what actions you took. To get rid of such warnings, you can remove the work directory and rebuild the recipe, as follows:

```
$ bitbake matchbox-desktop -c clean  
$ bitbake matchbox-desktop
```

You can view a list of tasks in a given package by running the *do\_listtasks* task as follows:

```
$ bitbake matchbox-desktop -c listtasks
```

The results appear as output to the console and are also in the file `${WORKDIR}/temp/log.do_listtasks`.

### 8.35.10 General BitBake Problems

You can see debug output from BitBake by using the `-D` option. The debug output gives more information about what BitBake is doing and the reason behind it. Each `-D` option you use increases the logging level. The most common usage is `-DDD`.

The output from `bitbake -DDD -v targetname` can reveal why BitBake chose a certain version of a package or why BitBake picked a certain provider. This command could also help you in a situation where you think BitBake did something unexpected.

### 8.35.11 Building with No Dependencies

To build a specific recipe (`.bb` file), you can use the following command form:

```
$ bitbake -b somepath/somerecipe.bb
```

This command form does not check for dependencies. Consequently, you should use it only when you know existing dependencies have been met.

**i Nota**

You can also specify fragments of the filename. In this case, BitBake checks for a unique match.

### 8.35.12 Recipe Logging Mechanisms

The Yocto Project provides several logging functions for producing debugging output and reporting errors and warnings. For Python functions, the following logging functions are available. All of these functions log to `${T}/log.do_task`, and can also log to standard output (stdout) with the right settings:

- `bb.plain(msg)`: Writes `msg` as is to the log while also logging to stdout.
- `bb.note(msg)`: Writes "NOTE: `msg`" to the log. Also logs to stdout if BitBake is called with "-v".
- `bb.debug(level, msg)`: Writes "DEBUG: `msg`" to the log. Also logs to stdout if the log level is greater than or equal to `level`. See the "Usage and syntax" option in the BitBake User Manual for more information.
- `bb.warn(msg)`: Writes "WARNING: `msg`" to the log while also logging to stdout.
- `bb.error(msg)`: Writes "ERROR: `msg`" to the log while also logging to standard out (stdout).

**i Nota**

Calling this function does not cause the task to fail.

- `bb.fatal(msg)`: This logging function is similar to `bb.error(msg)` but also causes the calling task to fail.

**i Nota**

`bb.fatal()` raises an exception, which means you do not need to put a "return" statement after the function.

The same logging functions are also available in shell functions, under the names `bbplain`, `bbnote`, `bbdebug`, `bbwarn`, `bberror`, and `bbfatal`. The `logging` class implements these functions. See that class in the `meta/classes` folder of *OpenEmbedded-Core (OE-Core)* for information.

### Logging With Python

When creating recipes using Python and inserting code that handles build logs, keep in mind the goal is to have informative logs while keeping the console as "silent" as possible. Also, if you want status messages in the log, use the "debug" loglevel.

Here is an example written in Python. The code handles logging for a function that determines the number of tasks needed to be run. See the "[do\\_listtasks](#)" section for additional information:

```
python do_listtasks() {
    bb.debug(2, "Starting to figure out the task list")
    if noteworthy_condition:
```

(continues on next page)

(continua dalla pagina precedente)

```

    bb.note("There are 47 tasks to run")
    bb.debug(2, "Got to point xyz")
    if warning_trigger:
        bb.warn("Detected warning_trigger, this might be a problem later.")
    if recoverable_error:
        bb.error("Hit recoverable_error, you really need to fix this!")
    if fatal_error:
        bb.fatal("fatal_error detected, unable to print the task list")
    bb.plain("The tasks present are abc")
    bb.debug(2, "Finished figuring out the tasklist")
}

```

## Logging With Bash

When creating recipes using Bash and inserting code that handles build logs, you have the same goals --- informative with minimal console output. The syntax you use for recipes written in Bash is similar to that of recipes written in Python described in the previous section.

Here is an example written in Bash. The code logs the progress of the `do_my_function` function:

```

do_my_function() {
    bbdebug 2 "Running do_my_function"
    if [ exceptional_condition ]; then
        bbnote "Hit exceptional_condition"
    fi
    bbdebug 2 "Got to point xyz"
    if [ warning_trigger ]; then
        bbwarn "Detected warning_trigger, this might cause a problem later."
    fi
    if [ recoverable_error ]; then
        bberror "Hit recoverable_error, correcting"
    fi
    if [ fatal_error ]; then
        bbfatal "fatal_error detected"
    fi
    bbdebug 2 "Completed do_my_function"
}

```

### 8.35.13 Debugging Parallel Make Races

A parallel make race occurs when the build consists of several parts that are run simultaneously and a situation occurs when the output or result of one part is not ready for use with a different part of the build that depends on that output. Parallel make races are annoying and can sometimes be difficult to reproduce and fix. However, there are some simple tips and tricks that can help you debug and fix them. This section presents a real-world example of an error encountered on the Yocto Project autobuilder and the process used to fix it.

**i Nota**

If you cannot properly fix a `make` race condition, you can work around it by clearing either the `PARALLEL_MAKE` or `PARALLEL_MAKEINST` variables.

**The Failure**

For this example, assume that you are building an image that depends on the "neard" package. And, during the build, BitBake runs into problems and creates the following output.

**i Nota**

This example log file has longer lines artificially broken to make the listing easier to read.

If you examine the output or the log file, you see the failure during `make`:

```
| DEBUG: SITE files ['endian-little', 'bit-32', 'ix86-common', 'common-linux',
↪ 'common-glibc', 'i586-linux', 'common']
| DEBUG: Executing shell function do_compile
| NOTE: make -j 16
| make --no-print-directory all-am
| /bin/mkdir -p include/near
| /bin/mkdir -p include/near
| /bin/mkdir -p include/near
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↪ poky-linux/neard/
| 0.14-r0/neard-0.14/include/types.h include/near/types.h
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↪ poky-linux/neard/
| 0.14-r0/neard-0.14/include/log.h include/near/log.h
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↪ poky-linux/neard/
| 0.14-r0/neard-0.14/include/plugin.h include/near/plugin.h
| /bin/mkdir -p include/near
| /bin/mkdir -p include/near
| /bin/mkdir -p include/near
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↪ poky-linux/neard/
| 0.14-r0/neard-0.14/include/tag.h include/near/tag.h
| /bin/mkdir -p include/near
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↪ poky-linux/neard/
| 0.14-r0/neard-0.14/include/adapt.h include/near/adapt.h
| /bin/mkdir -p include/near
```

(continues on next page)

(continua dalla pagina precedente)

```

| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/ndef.h include/near/ndef.h
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/tlv.h include/near/tlv.h
| /bin/mkdir -p include/near
| /bin/mkdir -p include/near
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/setting.h include/near/setting.h
| /bin/mkdir -p include/near
| /bin/mkdir -p include/near
| /bin/mkdir -p include/near
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/device.h include/near/device.h
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/nfc_copy.h include/near/nfc_copy.h
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/snep.h include/near/snep.h
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/version.h include/near/version.h
| ln -s /home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/work/i586-
↳poky-linux/neard/
  0.14-r0/neard-0.14/include/dbus.h include/near/dbus.h
| ./src/genbuiltin nfctype1 nfctype2 nfctype3 nfctype4 p2p > src/builtin.h
| i586-poky-linux-gcc -m32 -march=i586 --sysroot=/home/pokybuild/yocto-
↳autobuilder/nightly-x86/
  build/build/tmp/sysroots/qemux86 -DHAVE_CONFIG_H -I. -I./include -I./src -I./
↳gdbus -I/home/pokybuild/
  yocto-autobuilder/nightly-x86/build/build/tmp/sysroots/qemux86/usr/include/glib-
↳2.0
  -I/home/pokybuild/yocto-autobuilder/nightly-x86/build/build/tmp/sysroots/qemux86/
↳usr/
  lib/glib-2.0/include -I/home/pokybuild/yocto-autobuilder/nightly-x86/build/
↳build/
  tmp/sysroots/qemux86/usr/include/dbus-1.0 -I/home/pokybuild/yocto-autobuilder/
  nightly-x86/build/build/tmp/sysroots/qemux86/usr/lib/dbus-1.0/include -I/home/
↳pokybuild/yocto-autobuilder/

```

(continues on next page)

(continua dalla pagina precedente)

```

nightly-x86/build/build/tmp/sysroots/qemux86/usr/include/libnl3
-DNEAR_PLUGIN_BUILTIN -DPLUGINDIR=\"/usr/lib/near/plugins\"
-DCONFIGDIR=\"/etc/neard\" -O2 -pipe -g -feliminate-unused-debug-types -c
-o tools/snep-send.o tools/snep-send.c
| In file included from tools/snep-send.c:16:0:
| tools/./src/near.h:41:23: fatal error: near/dbus.h: No such file or directory
| #include <near/dbus.h>
|
| compilation terminated.
| make[1]: *** [tools/snep-send.o] Error 1
| make[1]: *** Waiting for unfinished jobs....
| make: *** [all] Error 2
| ERROR: oe_runmake failed

```

## Reproducing the Error

Because race conditions are intermittent, they do not manifest themselves every time you do the build. In fact, most times the build will complete without problems even though the potential race condition exists. Thus, once the error surfaces, you need a way to reproduce it.

In this example, compiling the "neard" package is causing the problem. So the first thing to do is build "neard" locally. Before you start the build, set the `PARALLEL_MAKE` variable in your `build/conf/local.conf` file to a high number (e.g. "-j 20"). Using a high value for `PARALLEL_MAKE` increases the chances of the race condition showing up:

```
$ bitbake neard
```

Once the local build for "neard" completes, start a devshell build:

```
$ bitbake neard -c devshell
```

For information on how to use a devshell, see the "[Using a Development Shell](#)" section.

In the devshell, do the following:

```
$ make clean
$ make tools/snep-send.o
```

The devshell commands cause the failure to clearly be visible. In this case, there is a missing dependency for the neard Makefile target. Here is some abbreviated, sample output with the missing dependency clearly visible at the end:

```

i586-poky-linux-gcc -m32 -march=i586 --sysroot=/home/scott-lenovo/.....
.
.
.
tools/snep-send.o

```

(continues on next page)



(continua dalla pagina precedente)

```
In file included from tools/snep-send.c:16:0:
tools/./src/near.h:41:23: fatal error: near/dbus.h: No such file or directory
#include <near/dbus.h>
                        ^
compilation terminated.
make: *** [tools/snep-send.o] Error 1
$
```

### Creating a Patch for the Fix

Because there is a missing dependency for the Makefile target, you need to patch the `Makefile.am` file, which is generated from `Makefile.in`. You can use Quilt to create the patch:

```
$ quilt new parallelmake.patch
Patch patches/parallelmake.patch is now on top
$ quilt add Makefile.am
File Makefile.am added to patch patches/parallelmake.patch
```

For more information on using Quilt, see the *"Using Quilt in Your Workflow"* section.

At this point you need to make the edits to `Makefile.am` to add the missing dependency. For our example, you have to add the following line to the file:

```
tools/snep-send.$(OBJEXT): include/near/dbus.h
```

Once you have edited the file, use the `refresh` command to create the patch:

```
$ quilt refresh
Refreshed patch patches/parallelmake.patch
```

Once the patch file is created, you need to add it back to the originating recipe folder. Here is an example assuming *OpenEmbedded-Core (OE-Core)* is named `openembedded-core`:

```
$ cp patches/parallelmake.patch openembedded-core/meta/recipes-connectivity/neard/
↪neard
```

The final thing you need to do to implement the fix in the build is to update the "neard" recipe (i.e. `neard-0.14.bb`) so that the `SRC_URI` statement includes the patch file. The recipe file is in the folder above the patch. Here is what the edited `SRC_URI` statement would look like:

```
SRC_URI = "${KERNELORG_MIRROR}/linux/network/nfc/${BPN}-${PV}.tar.xz \
          file://neard.in \
          file://neard.service.in \
          file://parallelmake.patch \
          "
```

With the patch complete and moved to the correct folder and the `SRC_URI` statement updated, you can exit the devshell:

```
$ exit
```

## Testing the Build

With everything in place, you can get back to trying the build again locally:

```
$ bitbake neard
```

This build should succeed.

Now you can open up a devshell again and repeat the clean and make operations as follows:

```
$ bitbake neard -c devshell
$ make clean
$ make tools/snep-send.o
```

The build should work without issue.

As with all solved problems, if they originated upstream, you need to submit the fix for the recipe in OE-Core and upstream so that the problem is taken care of at its source. See the "*Apportare Modifiche a un Componente*" section for more information.

### 8.35.14 Debugging With the GNU Project Debugger (GDB) Remotely

GDB allows you to examine running programs, which in turn helps you to understand and fix problems. It also allows you to perform post-mortem style analysis of program crashes. GDB is available as a package within the Yocto Project and is installed in SDK images by default. See the "*Immagini*" chapter in the Yocto Project Reference Manual for a description of these images. You can find information on GDB at <https://sourceware.org/gdb/>.

#### Nota

For best results, install debug (`-dbg`) packages for the applications you are going to debug. Doing so makes extra debug symbols available that give you more meaningful output.

Sometimes, due to memory or disk space constraints, it is not possible to use GDB directly on the remote target to debug applications. These constraints arise because GDB needs to load the debugging information and the binaries of the process being debugged. Additionally, GDB needs to perform many computations to locate information such as function names, variable names and values, stack traces and so forth --- even before starting the debugging process. These extra computations place more load on the target system and can alter the characteristics of the program being debugged.

To help get past the previously mentioned constraints, there are two methods you can use: running a debuginfod server and using gdbserver.

## Using the debuginfod server method

debuginfod from elfutils is a way to distribute debuginfo files. Running a debuginfod server makes debug symbols readily available, which means you don't need to download debugging information and the binaries of the process being debugged. You can just fetch debug symbols from the server.

To run a debuginfod server, you need to do the following:

- Ensure that debuginfod is present in *DISTRO\_FEATURES* (it already is in *OpenEmbedded-Core (OE-Core)* defaults and *Poky* reference distribution).

If not, set in your distro *configuration file* or in *build/conf/local.conf*:

```
DISTRO_FEATURES:append = " debuginfod"
```

This distro feature enables the server and client library in elfutils, and enables debuginfod support in clients (at the moment, gdb and binutils).

- Run the following commands to launch the debuginfod server on the host:

```
$ oe-debuginfod
```

- To use debuginfod on the target, you need to know the ip:port where debuginfod is listening on the host (port defaults to 8002), and export that into the shell environment, for example in qemu:

```
root@qemux86-64:~# export DEBUGINFOD_URLS="http://192.168.7.1:8002/"
```

- Then debug info fetching should simply work when running the target gdb, readelf or objdump, for example:

```
root@qemux86-64:~# gdb /bin/cat
...
Reading symbols from /bin/cat...
Downloading separate debug info for /bin/cat...
Reading symbols from /home/root/.cache/debuginfod_client/
→923dc4780cfbc545850c616bffa884b6b5eaf322/debuginfo...
```

- It's also possible to use debuginfod-find to just query the server:

```
root@qemux86-64:~# debuginfod-find debuginfo /bin/ls
/home/root/.cache/debuginfod_client/356edc585f7f82d46f94fcb87a86a3fe2d2e60bd/
→debuginfo
```

## Using the gdbserver method

gdbserver, which runs on the remote target and does not load any debugging information from the debugged process. Instead, a GDB instance processes the debugging information that is run on a remote computer - the host GDB. The host GDB then sends control commands to gdbserver to make it stop or start the debugged program, as well as read or write memory regions of that debugged program. All the debugging information loaded and processed as well as all the heavy debugging is done by the host GDB. Offloading these processes gives the gdbserver running on the target a chance to remain small and fast.

Because the host GDB is responsible for loading the debugging information and for doing the necessary processing to make actual debugging happen, you have to make sure the host can access the unstripped binaries complete with their debugging information and also be sure the target is compiled with no optimizations. The host GDB must also have local access to all the libraries used by the debugged program. Because gdbserver does not need any local debugging information, the binaries on the remote target can remain stripped. However, the binaries must also be compiled without optimization so they match the host's binaries.

To remain consistent with GDB documentation and terminology, the binary being debugged on the remote target machine is referred to as the "inferior" binary. For documentation on GDB see the [GDB site](#).

The following steps show you how to debug using the GNU project debugger.

1. *Configure your build system to construct the companion debug filesystem:*

In your *build/conf/local.conf* file, set the following:

```
IMAGE_GEN_DEBUGFS = "1"
IMAGE_FSTYPES_DEBUGFS = "tar.bz2"
```

These options cause the OpenEmbedded build system to generate a special companion filesystem fragment, which contains the matching source and debug symbols to your deployable filesystem. The build system does this by looking at what is in the deployed filesystem, and pulling the corresponding `-dbg` packages.

The companion debug filesystem is not a complete filesystem, but only contains the debug fragments. This filesystem must be combined with the full filesystem for debugging. Subsequent steps in this procedure show how to combine the partial filesystem with the full filesystem.

2. *Configure the system to include gdbserver in the target filesystem:*

Make the following addition in your *build/conf/local.conf* file:

```
EXTRA_IMAGE_FEATURES:append = " tools-debug"
```

The change makes sure the `gdbserver` package is included.

3. *Build the environment:*

Use the following command to construct the image and the companion Debug Filesystem:

```
$ bitbake image
```

Build the cross GDB component and make it available for debugging. Build the SDK that matches the image. Building the SDK is best for a production build that can be used later for debugging, especially during long term maintenance:

```
$ bitbake -c populate_sdk image
```

Alternatively, you can build the minimal toolchain components that match the target. Doing so creates a smaller than typical SDK and only contains a minimal set of components with which to build simple test applications, as well as run the debugger:

```
$ bitbake meta-toolchain
```

A final method is to build Gdb itself within the build system:

```
$ bitbake gdb-cross-<architecture>
```

Doing so produces a temporary copy of `cross-gdb` you can use for debugging during development. While this is the quickest approach, the two previous methods in this step are better when considering long-term maintenance strategies.

#### Nota

If you run `bitbake gdb-cross`, the OpenEmbedded build system suggests the actual image (e.g. `gdb-cross-i586`). The suggestion is usually the actual name you want to use.

#### 4. *Set up the debugfs:*

Run the following commands to set up the debugfs:

```
$ mkdir debugfs
$ cd debugfs
$ tar xvfj build-dir/tmp/deploy/images/machine/image.rootfs.tar.bz2
$ tar xvfj build-dir/tmp/deploy/images/machine/image-dbg.rootfs.tar.bz2
```

#### 5. *Set up GDB:*

Install the SDK (if you built one) and then source the correct environment file. Sourcing the environment file puts the SDK in your `PATH` environment variable and sets `$GDB` to the SDK's debugger.

If you are using the build system, Gdb is located in `build-dir/tmp/sysroots/host/usr/bin/architecture/architecture-gdb`

#### 6. *Boot the target:*

For information on how to run QEMU, see the [QEMU Documentation](#).

#### Nota

Be sure to verify that your host can access the target via TCP.

#### 7. *Debug a program:*

Debugging a program involves running `gdbserver` on the target and then running Gdb on the host. The example in this step debugs `gzip`:

```
root@qemux86:~# gdbserver localhost:1234 /bin/gzip --help
```

For additional `gdbserver` options, see the [GDB Server Documentation](#).

After running gdbserver on the target, you need to run Gdb on the host and configure it and connect to the target. Use these commands:

```
$ cd directory-holding-the-debugfs-directory
$ arch-gdb
(gdb) set sysroot debugfs
(gdb) set substitute-path /usr/src/debug debugfs/usr/src/debug
(gdb) target remote IP-of-target:1234
```

At this point, everything should automatically load (i.e. matching binaries, symbols and headers).

#### Nota

The Gdb `set` commands in the previous example can be placed into the users `~/.gdbinit` file. Upon starting, Gdb automatically runs whatever commands are in that file.

### 8. Deploying without a full image rebuild:

In many cases, during development you want a quick method to deploy a new binary to the target and debug it, without waiting for a full image build.

One approach to solving this situation is to just build the component you want to debug. Once you have built the component, copy the executable directly to both the target and the host `debugfs`.

If the binary is processed through the debug splitting in OpenEmbedded, you should also copy the debug items (i.e. `.debug` contents and corresponding `/usr/src/debug` files) from the work directory. Here is an example:

```
$ bitbake bash
$ bitbake -c devshell bash
$ cd ..
$ scp packages-split/bash/bin/bash target:/bin/bash
$ cp -a packages-split/bash-dbg/* path/debugfs
```

## 8.35.15 Debugging with the GNU Project Debugger (GDB) on the Target

The previous section addressed using GDB remotely for debugging purposes, which is the most usual case due to the inherent hardware limitations on many embedded devices. However, debugging in the target hardware itself is also possible with more powerful devices. This section describes what you need to do in order to support using GDB to debug on the target hardware.

To support this kind of debugging, you need do the following:

- Ensure that GDB is on the target. You can do this by making the following addition to your `build/conf/local.conf` file:

```
EXTRA_IMAGE_FEATURES:append = " tools-debug"
```

- Ensure that debug symbols are present. You can do so by adding the corresponding `-dbg` package to *IMAGE\_INSTALL*:

```
IMAGE_INSTALL:append = " packagename-dbg"
```

Alternatively, you can add the following to *build/conf/local.conf* to include all the debug symbols:

```
EXTRA_IMAGE_FEATURES:append = " dbg-pkgs"
```

#### **i** Nota

To improve the debug information accuracy, you can reduce the level of optimization used by the compiler. For example, when adding the following line to your *build/conf/local.conf* file, you will reduce optimization from *FULL\_OPTIMIZATION* of `"-O2"` to *DEBUG\_OPTIMIZATION* of `"-O -fno-omit-frame-pointer"`:

```
DEBUG_BUILD = "1"
```

Consider that this will reduce the application's performance and is recommended only for debugging purposes.

### 8.35.16 Enabling Minidebuginfo

Enabling the *DISTRO\_FEATURES* `minidebuginfo` adds a compressed ELF section `.gnu_debugdata` to all binary files, containing only function names, and thus increasing the size of the binaries only by 5 to 10%. For comparison, full debug symbols can be 10 times as big as a stripped binary, and it is thus not always possible to deploy full debug symbols. Minidebuginfo data allows, on the one side, to retrieve a call-stack using GDB (command `backtrace`) without deploying full debug symbols to the target. It also allows to retrieve a symbolicated call-stack when using `systemd-coredump` to manage coredumps (commands `coredumpctl list` and `coredumpctl info`).

This feature was created by Fedora, see <https://fedoraproject.org/wiki/Features/MiniDebugInfo> for more details.

### 8.35.17 Other Debugging Tips

Here are some other tips that you might find useful:

- When adding new packages, it is worth watching for undesirable items making their way into compiler command lines. For example, you do not want references to local system files like `/usr/lib/` or `/usr/include/`.
- If you want to remove the `psplash` boot splashscreen, add `psplash=false` to the kernel command line. Doing so prevents `psplash` from loading and thus allows you to see the console. It is also possible to switch out of the splashscreen by switching the virtual console (e.g. `Fn+Left` or `Fn+Right` on a Zaurus).
- Removing *TMPDIR* (usually `tmp/`, within the *Build Directory*) can often fix temporary build issues. Removing *TMPDIR* is usually a relatively cheap operation, because task output will be cached in *SSTATE\_DIR* (usually `sstate-cache/`, which is also in the *Build Directory*).

**i Nota**

Removing *TMPDIR* might be a workaround rather than a fix. Consequently, trying to determine the underlying cause of an issue before removing the directory is a good idea.

- Understanding how a feature is used in practice within existing recipes can be very helpful. It is recommended that you configure some method that allows you to quickly search through files.

Using GNU Grep, you can use the following shell function to recursively search through common recipe-related files, skipping binary files, `.git` directories, and the *Build Directory* (assuming its name starts with "build"):

```
g() {
    grep -Ir \
        --exclude-dir=.git \
        --exclude-dir='build*' \
        --include='*.bb*' \
        --include='*.inc*' \
        --include='*.conf*' \
        --include='*.py*' \
        "$@"
}
```

Here are some usage examples:

```
$ g FOO # Search recursively for "FOO"
$ g -i foo # Search recursively for "foo", ignoring case
$ g -w FOO # Search recursively for "FOO" as a word, ignoring e.g. "FOOBAR"
```

If figuring out how some feature works requires a lot of searching, it might indicate that the documentation should be extended or improved. In such cases, consider filing a documentation bug using the Yocto Project implementation of *Bugzilla*. For information on how to submit a bug against the Yocto Project, see the Yocto Project Bugzilla [wiki page](#) and the "*Segnalazione di un Difetto in Yocto Project e in OpenEmbedded*" section.

**i Nota**

The manuals might not be the right place to document variables that are purely internal and have a limited scope (e.g. internal variables used to implement a single `.bbclass` file).

## 8.36 Working With Licenses

As mentioned in the "*Licenze*" section in the Yocto Project Overview and Concepts Manual, open source projects are open to the public and they consequently have different licensing structures in place. This section describes the mechanism by which the *OpenEmbedded Build System* tracks changes to licensing text and covers how to maintain open source license compliance during your project's lifecycle. The section also describes how to enable commercially licensed recipes, which by default are disabled.



### 8.36.1 Tracking License Changes

The license of an upstream project might change in the future. In order to prevent these changes going unnoticed, the `LIC_FILES_CHKSUM` variable tracks changes to the license text. The checksums are validated at the end of the configure step, and if the checksums do not match, the build will fail.

#### Specifying the `LIC_FILES_CHKSUM` Variable

The `LIC_FILES_CHKSUM` variable contains checksums of the license text in the source code for the recipe. Here is an example of how to specify `LIC_FILES_CHKSUM`:

```
LIC_FILES_CHKSUM = "file://COPYING;md5=xxxx \
                    file://licfile1.txt;beginline=5;endline=29;md5=yyyy \
                    file://licfile2.txt;endline=50;md5=zzzz \
                    ..."
```

#### Nota

- When using "beginline" and "endline", realize that line numbering begins with one and not zero. Also, the included lines are inclusive (i.e. lines five through and including 29 in the previous example for `licfile1.txt`).
- When a license check fails, the selected license text is included as part of the QA message. Using this output, you can determine the exact start and finish for the needed license text.

The build system uses the `S` variable as the default directory when searching files listed in `LIC_FILES_CHKSUM`. The previous example employs the default directory.

Consider this next example:

```
LIC_FILES_CHKSUM = "file://src/ls.c;beginline=5;endline=16;\
                    md5=bb14ed3c4cda583abc85401304b5cd4e"
LIC_FILES_CHKSUM = "file://${UNPACKDIR}/license.html;
                    ↪md5=5c94767cedb5d6987c902ac850ded2c6"
```

The first line locates a file in `${S}/src/ls.c` and isolates lines five through 16 as license text. The second line refers to a file in `UNPACKDIR`.

Note that `LIC_FILES_CHKSUM` variable is mandatory for all recipes, unless the `LICENSE` variable is set to "CLOSED".

#### Explanation of Syntax

As mentioned in the previous section, the `LIC_FILES_CHKSUM` variable lists all the important files that contain the license text for the source code. It is possible to specify a checksum for an entire file, or a specific section of a file (specified by beginning and ending line numbers with the "beginline" and "endline" parameters, respectively). The latter is useful for source files with a license notice header, README documents, and so forth. If you do not use the

"beginline" parameter, then it is assumed that the text begins on the first line of the file. Similarly, if you do not use the "endline" parameter, it is assumed that the license text ends with the last line of the file.

The "md5" parameter stores the md5 checksum of the license text. If the license text changes in any way as compared to this parameter then a mismatch occurs. This mismatch triggers a build failure and notifies the developer. Notification allows the developer to review and address the license text changes. Also note that if a mismatch occurs during the build, the correct md5 checksum is placed in the build log and can be easily copied to the recipe.

There is no limit to how many files you can specify using the `LIC_FILES_CHKSUM` variable. Generally, however, every project requires a few specifications for license tracking. Many projects have a "COPYING" file that stores the license information for all the source code files. This practice allows you to just track the "COPYING" file as long as it is kept up to date.

#### Nota

- If you specify an empty or invalid "md5" parameter, *BitBake* returns an md5 mis-match error and displays the correct "md5" parameter value during the build. The correct parameter is also captured in the build log.
- If the whole file contains only license text, you do not need to use the "beginline" and "endline" parameters.

## 8.36.2 Enabling Commercially Licensed Recipes

By default, the OpenEmbedded build system disables components that have commercial or other special licensing requirements. Such requirements are defined on a recipe-by-recipe basis through the `LICENSE_FLAGS` variable definition in the affected recipe. For instance, the `meta/recipes-multimedia/gstreamer/gstreamer1.0-plugins-ugly` recipe of *OpenEmbedded-Core (OE-Core)* contains the following statement:

```
LICENSE_FLAGS = "commercial"
```

Here is a slightly more complicated example that contains both an explicit recipe name and version (after variable expansion):

```
LICENSE_FLAGS = "license_${PN}_${PV}"
```

It is possible to give more details about a specific license using flags on the `LICENSE_FLAGS_DETAILS` variable:

```
LICENSE_FLAGS_DETAILS[my-eula-license] = "For further details, see https://example.  
↪com/eula."
```

If set, this will be displayed to the user if the license hasn't been accepted.

In order for a component restricted by a `LICENSE_FLAGS` definition to be enabled and included in an image, it needs to have a matching entry in the global `LICENSE_FLAGS_ACCEPTED` variable, which is a variable typically defined in your `build/conf/local.conf` file. For example, to enable the `meta/recipes-multimedia/gstreamer/gstreamer1.0-plugins-ugly` package of *OpenEmbedded-Core (OE-Core)*, you could add either the string "commercial\_gst-plugins-ugly" or the more general string "commercial" to `LICENSE_FLAGS_ACCEPTED`. See the "License Flag Matching" section for a full explanation of how `LICENSE_FLAGS` matching works. Here is the example:

```
LICENSE_FLAGS_ACCEPTED = "commercial_gst-plugins-ugly"
```

Likewise, to additionally enable the package built from the recipe containing `LICENSE_FLAGS = "license_${PN}_${PV}"`, and assuming that the actual recipe name was `emgd_1.10.bb`, the following string would enable that package as well as the original `gst-plugins-ugly` package:

```
LICENSE_FLAGS_ACCEPTED = "commercial_gst-plugins-ugly license_emgd_1.10"
```

As a convenience, you do not need to specify the complete license string for every package. You can use an abbreviated form, which consists of just the first portion or portions of the license string before the initial underscore character or characters. A partial string will match any license that contains the given string as the first portion of its license. For example, the following value will also match both of the packages previously mentioned as well as any other packages that have licenses starting with "commercial" or "license":

```
LICENSE_FLAGS_ACCEPTED = "commercial license"
```

## License Flag Matching

License flag matching allows you to control what recipes the OpenEmbedded build system includes in the build. Fundamentally, the build system attempts to match *LICENSE\_FLAGS* strings found in recipes against strings found in *LICENSE\_FLAGS\_ACCEPTED*. A match causes the build system to include a recipe in the build, while failure to find a match causes the build system to exclude a recipe.

In general, license flag matching is simple. However, understanding some concepts will help you correctly and effectively use matching.

Before a flag defined by a particular recipe is tested against the entries of *LICENSE\_FLAGS\_ACCEPTED*, the expanded string `_${PN}` is appended to the flag. This expansion makes each *LICENSE\_FLAGS* value recipe-specific. After expansion, the string is then matched against the entries. Thus, specifying `LICENSE_FLAGS = "commercial"` in recipe "foo", for example, results in the string `"commercial_foo"`. And, to create a match, that string must appear among the entries of *LICENSE\_FLAGS\_ACCEPTED*.

Judicious use of the *LICENSE\_FLAGS* strings and the contents of the *LICENSE\_FLAGS\_ACCEPTED* variable allows you a lot of flexibility for including or excluding recipes based on licensing. For example, you can broaden the matching capabilities by using license flags string subsets in *LICENSE\_FLAGS\_ACCEPTED*.

### Nota

When using a string subset, be sure to use the part of the expanded string that precedes the appended underscore character (e.g. `usethispart_1.3`, `usethispart_1.4`, and so forth).

For example, simply specifying the string "commercial" in the *LICENSE\_FLAGS\_ACCEPTED* variable matches any expanded *LICENSE\_FLAGS* definition that starts with the string "commercial" such as `"commercial_foo"` and `"commercial_bar"`, which are the strings the build system automatically generates for hypothetical recipes named "foo" and "bar" assuming those recipes simply specify the following:

```
LICENSE_FLAGS = "commercial"
```

Thus, you can choose to exhaustively enumerate each license flag in the list and allow only specific recipes into the image, or you can use a string subset that causes a broader range of matches to allow a range of recipes into the image.

This scheme works even if the `LICENSE_FLAGS` string already has `_${PN}` appended. For example, the build system turns the license flag "commercial\_1.2\_foo" into "commercial\_1.2\_foo\_foo" and would match both the general "commercial" and the specific "commercial\_1.2\_foo" strings found in the `LICENSE_FLAGS_ACCEPTED` variable, as expected.

Here are some other scenarios:

- You can specify a versioned string in the recipe such as "commercial\_foo\_1.2" in a "foo" recipe. The build system expands this string to "commercial\_foo\_1.2\_foo". Combine this license flag with a `LICENSE_FLAGS_ACCEPTED` variable that has the string "commercial" and you match the flag along with any other flag that starts with the string "commercial".
- Under the same circumstances, you can add "commercial\_foo" in the `LICENSE_FLAGS_ACCEPTED` variable and the build system not only matches "commercial\_foo\_1.2" but also matches any license flag with the string "commercial\_foo", regardless of the version.
- You can be very specific and use both the package and version parts in the `LICENSE_FLAGS_ACCEPTED` list (e.g. "commercial\_foo\_1.2") to specifically match a versioned recipe.

## Other Variables Related to Commercial Licenses

There are other helpful variables related to commercial license handling, defined in the `meta/conf/distro/include/default-distrovars.inc` file in *OpenEmbedded-Core (OE-Core)*:

```
COMMERCIAL_AUDIO_PLUGINS ?= ""  
COMMERCIAL_VIDEO_PLUGINS ?= ""
```

If you want to enable these components, you can do so by making sure you have statements similar to the following in your `build/conf/local.conf` configuration file:

```
COMMERCIAL_AUDIO_PLUGINS = "gst-plugins-ugly-mad \  
    gst-plugins-ugly-mpegaudioparse"  
COMMERCIAL_VIDEO_PLUGINS = "gst-plugins-ugly-mpeg2dec \  
    gst-plugins-ugly-mpegstream gst-plugins-bad-mpegvideoparse"  
LICENSE_FLAGS_ACCEPTED = "commercial_gst-plugins-ugly commercial_gst-plugins-bad_  
↪commercial_qmmp"
```

Of course, you could also create a matching list for those components using the more general "commercial" string in the `LICENSE_FLAGS_ACCEPTED` variable, but that would also enable all the other packages with `LICENSE_FLAGS` containing "commercial", which you may or may not want:

```
LICENSE_FLAGS_ACCEPTED = "commercial"
```

Specifying audio and video plugins as part of the `COMMERCIAL_AUDIO_PLUGINS` and `COMMERCIAL_VIDEO_PLUGINS` statements (along with `LICENSE_FLAGS_ACCEPTED`) includes the plugins or components into built images, thus adding support for media formats or components.

#### Nota

GStreamer "ugly" and "bad" plugins are actually available through open source licenses. However, the "ugly" ones can be subject to software patents in some countries, making it necessary to pay licensing fees to distribute them. The "bad" ones are just deemed unreliable by the GStreamer community and should therefore be used with care.

### 8.36.3 Maintaining Open Source License Compliance During Your Product's Lifecycle

One of the concerns for a development organization using open source software is how to maintain compliance with various open source licensing during the lifecycle of the product. While this section does not provide legal advice or comprehensively cover all scenarios, it does present methods that you can use to assist you in meeting the compliance requirements during a software release.

With hundreds of different open source licenses that the Yocto Project tracks, it is difficult to know the requirements of each and every license. However, the requirements of the major FLOSS licenses can begin to be covered by assuming that there are three main areas of concern:

- Source code must be provided.
- License text for the software must be provided.
- Compilation scripts and modifications to the source code must be provided.

There are other requirements beyond the scope of these three and the methods described in this section (e.g. the mechanism through which source code is distributed).

As different organizations have different ways of releasing software, there can be multiple ways of meeting license obligations. At least, we describe here two methods for achieving compliance:

- The first method is to use OpenEmbedded's ability to provide the source code, provide a list of licenses, as well as compilation scripts and source code modifications.

The remainder of this section describes supported methods to meet the previously mentioned three requirements.

- The second method is to generate a *Software Bill of Materials (SBoM)*, as described in the "*Creating a Software Bill of Materials*" section. Not only do you generate *SPDX* output which can be used meet license compliance requirements (except for sharing the build system and layers sources for the time being), but this output also includes component version and patch information which can be used for vulnerability assessment.

Whatever method you choose, prior to releasing images, sources, and the build system, you should audit all artifacts to ensure completeness.

**i Nota**

The Yocto Project generates a license manifest during image creation that is located in `${DEPLOY_DIR}/licenses/${SSTATE_PKGARCH}/<image-name>-<machine>.rootfs-<datestamp>/` to assist with any audits.

## Providing the Source Code

Compliance activities should begin before you generate the final image. The first thing you should look at is the requirement that tops the list for most compliance groups --- providing the source. The Yocto Project has a few ways of meeting this requirement.

One of the easiest ways to meet this requirement is to provide the entire *DL\_DIR* used by the build. This method, however, has a few issues. The most obvious is the size of the directory since it includes all sources used in the build and not just the source used in the released image. It will include toolchain source, and other artifacts, which you would not generally release. However, the more serious issue for most companies is accidental release of proprietary software. The Yocto Project provides an *archiver* class to help avoid some of these concerns.

Before you employ *DL\_DIR* or the *archiver* class, you need to decide how you choose to provide source.

One way of doing this (but certainly not the only way) is to release just the source as a tarball. You can do this by adding the following to the *build/conf/local.conf* file found in the *Build Directory*:

```
INHERIT += "archiver"
ARCHIVER_MODE[src] = "original"
```

During the creation of your image, the source from all recipes that deploy packages to the image is placed within subdirectories of `DEPLOY_DIR/sources` based on the *LICENSE* for each recipe. Releasing the entire directory enables you to comply with requirements concerning providing the unmodified source. It is important to note that the size of the directory can get large.

A way to help mitigate the size issue is to only release tarballs for licenses that require the release of source. Let us assume you are only concerned with GPL code as identified by running the following script:

```
# Script to archive a subset of packages matching specific license(s)
# Source and license files are copied into sub folders of package folder
# Must be run from build folder
#!/bin/bash
src_release_dir="source-release"
mkdir -p $src_release_dir
for a in tmp/deploy/sources/*; do
    for d in $a/*; do
        # Get package name from path
        p=`basename $d`
        p=${p%-*}
        p=${p%-*}
        # Only archive GPL packages (update *GPL* regex for your license check)
```

(continues on next page)

(continua dalla pagina precedente)

```

numfiles=`ls tmp/deploy/licenses/$p/*GPL* 2> /dev/null | wc -l`
if [ $numfiles -ge 1 ]; then
    echo Archiving $p
    mkdir -p $src_release_dir/$p/source
    cp $d/* $src_release_dir/$p/source 2> /dev/null
    mkdir -p $src_release_dir/$p/license
    cp tmp/deploy/licenses/$p/* $src_release_dir/$p/license 2> /dev/null
fi
done
done

```

At this point, you could create a tarball from the `gpl_source_release` directory and provide that to the end user. This method would be a step toward achieving compliance with section 3a of GPLv2 and with section 6 of GPLv3.

## Providing License Text

One requirement that is often overlooked is inclusion of license text. This requirement also needs to be dealt with prior to generating the final image. Some licenses require the license text to accompany the binary. You can achieve this by adding the following to your *build/conf/local.conf* file or distro *configuration file*:

```

COPY_LIC_MANIFEST = "1"
COPY_LIC_DIRS = "1"
LICENSE_CREATE_PACKAGE = "1"

```

Adding these statements to the configuration file ensures that the licenses collected during package generation are included on your image.

### Nota

Setting all three variables to "1" results in the image having two copies of the same license file. One copy resides in `/usr/share/common-licenses` and the other resides in `/usr/share/license`.

The reason for this behavior is because *COPY\_LIC\_DIRS* and *COPY\_LIC\_MANIFEST* add a copy of the license when the image is built but do not offer a path for adding licenses for newly installed packages to an image. *LICENSE\_CREATE\_PACKAGE* adds a separate package and an upgrade path for adding licenses to an image.

As the source *archiver* class has already archived the original unmodified source that contains the license files, you would have already met the requirements for inclusion of the license information with source as defined by the GPL and other open source licenses.

## Providing Compilation Scripts and Source Code Modifications

At this point, we have addressed all we need prior to generating the image. The next two requirements are addressed during the final packaging of the release.

By releasing the version of the OpenEmbedded build system and the layers used during the build, you will be providing both compilation scripts and the source code modifications in one step.

If the deployment team has a [Layer BSP](#) and a distro layer, and those layers are used to patch, compile, package, or modify (in any way) any open source software included in your released images, you might be required to release those layers under section 3 of GPLv2 or section 1 of GPLv3. One way of doing that is with a clean checkout of the version of the Yocto Project and layers used during your build. Archiving a Git repository can be done with the `git-archive` command.

One thing a development organization might want to consider for end-user convenience is to provide its own version of the `meta/conf/templates/default/bblayers.conf.sample` file to ensure that when the end user utilizes the released build system to build an image, the development organization's layers are included in the `build/conf/bblayers.conf` file automatically:

```
# POKY_BBLAYERS_CONF_VERSION is increased each time build/conf/bblayers.conf
# changes incompatibly
POKY_BBLAYERS_CONF_VERSION = "2"

BBPATH = "${TOPDIR}"
BBFILES ?= ""

BBLAYERS ?= " \
    ##OEROOT##/meta \
    ##OEROOT##/../meta-yocto/meta-poky \
    ##OEROOT##/../meta-yocto/meta-yocto-bsp \
    ##OEROOT##/../meta-mylayer \
    "
```

Creating and providing an archive of the [Metadata](#) layers (recipes, configuration files, and so forth) enables you to meet your requirements to include the scripts to control compilation as well as any modifications to the original source.

### Compliance Limitations with Executables Built from Static Libraries

When package A is added to an image via the [RDEPENDS](#) or [RRECOMMENDS](#) mechanisms as well as explicitly included in the image recipe with `IMAGE_INSTALL`, and depends on a static linked library recipe B (`DEPENDS += "B"`), package B will neither appear in the generated license manifest nor in the generated source tarballs. This occurs as the [license](#) and [archiver](#) classes assume that only packages included via [RDEPENDS](#) or [RRECOMMENDS](#) end up in the image.

As a result, potential obligations regarding license compliance for package B may not be met.

The Yocto Project doesn't enable static libraries by default, in part because of this issue. Before a solution to this limitation is found, you need to keep in mind that if your root filesystem is built from static libraries, you will need to manually ensure that your deliveries are compliant with the licenses of these libraries.



### 8.36.4 Copying Non Standard Licenses

Some packages, such as the linux-firmware package, have many licenses that are not in any way common. You can avoid adding a lot of these types of common license files, which are only applicable to a specific package, by using the `NO_GENERIC_LICENSE` variable. Using this variable also avoids QA errors when you use a non-common, non-CLOSED license in a recipe.

Here is an example that uses the `LICENSE.Abilis.txt` file as the license from the fetched source:

```
NO_GENERIC_LICENSE[Firmware-Abilis] = "LICENSE.Abilis.txt"
```

## 8.37 Creating a Software Bill of Materials

Once you are able to build an image for your project, once the licenses for each software component are all identified (see "[Working With Licenses](#)") and once vulnerability fixes are applied (see "[Verifica delle Vulnerabilità](#)"), the OpenEmbedded build system can generate a description of all the components you used, their licenses, their dependencies, their sources, the changes that were applied to them and the known vulnerabilities that were fixed.

This description is generated in the form of a *Software Bill of Materials (SBOM)*, using the `SPDX` standard.

When you release software, this is the most standard way to provide information about the Software Supply Chain of your software image and SDK. The `SBOM` tooling is often used to ensure open source license compliance by providing the license texts used in the product which legal departments and end users can read in standardized format.

`SBOM` information is also critical to performing vulnerability exposure assessments, as all the components used in the Software Supply Chain are listed.

The OpenEmbedded build system generates such information by default (by inheriting the `create-spdx` class in `INHERIT_DISTRO`).

If needed, it can be disabled from a *configuration file*:

```
INHERIT_DISTRO:remove = "create-spdx"
```

There are two ways to generate SBOM metadata:

- By building an image, you will then get the `SPDX` output in JSON format as an `IMAGE-MACHINE.spdx.json` file in `tmp/deploy/images/MACHINE/` inside the *Build Directory*.
- By generating the SBOM document using the recipe metadata only:

```
$ bitbake <recipe> -c create_recipe_sbom
```

Note that recipe SBOM is also included in the image SBOM document (for the recipes involved in the build of the image only).

The `create-spdx` class offers options to include more information in the output `SPDX` data:

- Make the json files more human readable by setting (`SPDX_PRETTY`).
- Add a description of the source files used to generate host tools and target packages (`SPDX_INCLUDE_SOURCES`)

- Add a description of the **compiled** source files used to generate host tools and target packages (*SPDX\_INCLUDE\_COMPILED\_SOURCES*).
- Export the Linux kernel configuration (*CONFIG\_\** parameters) into the SPDX document (*SPDX\_INCLUDE\_KERNEL\_CONFIG*).
- Export the recipe's *PACKAGECONFIG* features (enabled/disabled) into the SPDX document (*SPDX\_INCLUDE\_PACKAGECONFIG*).
- Exclude specific files from the SPDX output using Python regular expressions (*SPDX\_FILE\_EXCLUDE\_PATTERNS*).
- Attach supplier information to the image SBOM, SDK SBOM, or individual packages (*SPDX\_IMAGE\_SUPPLIER*, *SPDX\_SDK\_SUPPLIER*, *SPDX\_PACKAGE\_SUPPLIER*).
- Enrich source downloads with ecosystem-specific Package URLs (PURLs), using the *cargo\_common*, *go-mod*, *pypi*, *npm*, and *cpan\** classes to automatically populate PURL identifiers for the corresponding language ecosystems.
- Record which agent invoked the build and on whose behalf it ran, enabling CI/CD traceability in the SBOM (*SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD*, *SPDX\_INVOKED\_BY*, *SPDX\_ON\_BEHALF\_OF*).

See also the *SPDX\_CUSTOM\_ANNOTATION\_VARS* variable which allows to associate custom notes to a recipe. See the [tools](#) page on the *SPDX* project website for a list of tools to consume and transform the *SPDX* data generated by the OpenEmbedded build system.

See the definition of the variables starting with *SPDX\_* in the *Yocto Project Reference Manual glossary* for more information.

See also Joshua Watt's presentations [Automated SBoM generation with OpenEmbedded and the Yocto Project at FOSDEM 2023](#) and [SPDX in the Yocto Project at FOSDEM 2024](#).

## 8.38 Using the Error Reporting Tool

The error reporting tool allows you to submit errors encountered during builds to a central database. Outside of the build environment, you can use a web interface to browse errors, view statistics, and query for errors. The tool works using a client-server system where the client portion is integrated in *OpenEmbedded-Core (OE-Core)*. The server receives the information collected and saves it in a database.

There is a live instance of the error reporting server at <https://errors.yoctoproject.org>. When you want to get help with build failures, you can submit all of the information on the failure easily and then point to the URL in your bug report or send an email to the mailing list.

**i Nota**

If you send error reports to this server, the reports become publicly visible.

### 8.38.1 Enabling and Using the Tool

By default, the error reporting tool is disabled. You can enable it by inheriting the *report-error* class by adding the following statement to the end of your *build/conf/local.conf* file in your *Build Directory*:

```
INHERIT += "report-error"
```

By default, the error reporting feature stores information in `${LOG_DIR}/error-report`. However, you can specify a directory to use by adding the following to your *build/conf/local.conf* file:

```
ERR_REPORT_DIR = "path"
```

Enabling error reporting causes the build process to collect the errors and store them in a file as previously described. When the build system encounters an error, it includes a command as part of the console output. You can run the command to send the error file to the server. For example, the following command sends the errors to an upstream server:

```
$ send-error-report /home/brandusa/project/poky/build/tmp/log/error-report/error_
↪report_201403141617.txt
```

In the previous example, the errors are sent to a public database available at <https://errors.yoctoproject.org>, which is used by the entire community. If you specify a particular server, you can send the errors to a different database. Use the following command for more information on available options:

```
$ send-error-report --help
```

When sending the error file, you are prompted to review the data being sent as well as to provide a name and optional email address. Once you satisfy these prompts, the command returns a link from the server that corresponds to your entry in the database. For example, here is a typical link: <https://errors.yoctoproject.org/Errors/Details/9522/>

Following the link takes you to a web interface where you can browse, query the errors, and view statistics.

### 8.38.2 Disabling the Tool

To disable the error reporting feature, simply remove or comment out the following statement from the end of your *build/conf/local.conf* file in your *Build Directory*:

```
INHERIT += "report-error"
```

### 8.38.3 Setting Up Your Own Error Reporting Server

If you want to set up your own error reporting server, you can obtain the code from the Git repository at <https://git.yoctoproject.org/error-report-web/>. Instructions on how to set it up are in the README document.

## 8.39 Using Wayland and Weston

Wayland is a computer display server protocol that provides a method for compositing window managers to communicate directly with applications and video hardware and expects them to communicate with input hardware using other libraries. Using Wayland with supporting targets can result in better control over graphics frame rendering than an application might otherwise achieve.

The Yocto Project provides the Wayland protocol libraries and the reference Weston compositor as part of its release. You can find the integrated packages in the meta layer of *OpenEmbedded-Core (OE-Core)*. Specifically, you can find the recipes that build both Wayland and Weston at `meta/recipes-graphics/wayland`.

You can build both the Wayland and Weston packages for use only with targets that accept the Mesa 3D and Direct Rendering Infrastructure, which is also known as Mesa DRI. This implies that you cannot build and use the packages if your target uses, for example, the Intel Embedded Media and Graphics Driver (Intel EMGD) that overrides Mesa DRI.

#### Nota

Due to lack of EGL support, Weston 1.0.3 will not run directly on the emulated QEMU hardware. However, this version of Weston will run under X emulation without issues.

This section describes what you need to do to implement Wayland and use the Weston compositor when building an image for a supporting target.

### 8.39.1 Enabling Wayland in an Image

To enable Wayland, you need to enable it to be built and enable it to be included (installed) in the image.

#### Building Wayland

To cause Mesa to build the `wayland-egl` platform and Weston to build Wayland with Kernel Mode Setting (KMS) support, include the "wayland" flag in the *DISTRO\_FEATURES* statement in your distro *configuration file*:

```
DISTRO_FEATURES:append = " wayland"
```

**i Nota**

If X11 has been enabled elsewhere, Weston will build Wayland with X11 support

## Installing Wayland and Weston

To install the Wayland feature into an image, you must include the following `CORE_IMAGE_EXTRA_INSTALL` statement in your distro *configuration file*:

```
CORE_IMAGE_EXTRA_INSTALL += "wayland weston"
```

### 8.39.2 Running Weston

To run Weston inside X11, enabling it as described earlier and building a Sato image is sufficient. If you are running your image under Sato, a Weston Launcher appears in the "Utility" category.

Alternatively, you can run Weston through the command-line interpreter (CLI), which is better suited for development work. To run Weston under the CLI, you need to do the following after your image is built:

1. Run these commands to export `XDGL_RUNTIME_DIR`:

```
mkdir -p /tmp/$USER-weston
chmod 0700 /tmp/$USER-weston
export XDGL_RUNTIME_DIR=/tmp/$USER-weston
```

2. Launch Weston in the shell:

```
weston
```

## 8.40 Using the Quick EMUlator (QEMU)

The Yocto Project uses an implementation of the Quick EMUlator (QEMU) Open Source project as part of the Yocto Project development "tool set". This chapter provides both procedures that show you how to use the Quick EMUlator (QEMU) and other QEMU information helpful for development purposes.

### 8.40.1 Overview

Within the context of the Yocto Project, QEMU is an emulator and virtualization machine that allows you to run a complete image you have built using the Yocto Project as just another task on your build system. QEMU is useful for running and testing images and applications on supported Yocto Project architectures without having actual hardware. Among other things, the Yocto Project uses QEMU to run automated Quality Assurance (QA) tests on final images shipped with each release.

**i Nota**

This implementation is not the same as QEMU in general.

This section provides a brief reference for the Yocto Project implementation of QEMU.

For official information and documentation on QEMU in general, see the following references:

- [QEMU Website](#): The official website for the QEMU Open Source project.
- [Documentation](#): The QEMU user manual.

## 8.40.2 Running QEMU

To use QEMU, you need to have QEMU installed and initialized as well as have the proper artifacts (i.e. image files and root filesystems) available. Follow these general steps to run QEMU:

1. *Install QEMU*: QEMU is made available with the Yocto Project a number of ways. One method is to install a Software Development Kit (SDK). See "[The QEMU Emulator](#)" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual for information on how to install QEMU.
2. *Setting Up the Environment*: How you set up the QEMU environment depends on how you installed QEMU:

- If you followed [Setting Up to Use the Yocto Project](#), either use `bitbake-setup` or source the environment setup script manually:

```
$ cd bitbake-builds
$ source layers/openembedded-core/oe-init-build-env
```

- If you installed a cross-toolchain, you can run the script that initializes the toolchain. For example, the following commands run the initialization script from the default `poky_sdk` directory:

```
. poky_sdk/environment-setup-core2-64-poky-linux
```

3. *Ensure the Artifacts are in Place*: You need to be sure you have a pre-built kernel that will boot in QEMU. You also need the target root filesystem for your target machine's architecture:
  - If you have previously built an image for QEMU (e.g. `qemux86`, `qemuarm`, and so forth), then the artifacts are in place in your [Build Directory](#).
  - If you have not built an image, you can go to the [machines/qemu](#) area and download a pre-built image that matches your architecture and can be run on QEMU.

See the "[Extracting the Root Filesystem](#)" section in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual for information on how to extract a root filesystem.

4. *Run QEMU*: The basic `runqemu` command syntax is as follows:

```
$ runqemu [option ] [...]
```

Based on what you provide on the command line, `runqemu` does a good job of figuring out what you are trying to do. For example, by default, QEMU looks for the most recently built image according to the timestamp when it needs to look for an image. Minimally, through the use of options, you must provide either a machine name, a virtual machine image (`*wic.vmdk`), or a kernel image (`*.bin`).

Here are some additional examples to help illustrate further QEMU:

- This example starts QEMU with `MACHINE` set to "qemux86-64". Assuming a standard [Build Directory](#), `runqemu` automatically finds the `bzImage-qemux86-64.bin` image file and the `core-image-minimal-qemux86-64-20200218002850.rootfs.ext4` (assuming the current build created a `core-image-minimal` image):

```
$ runqemu qemux86-64
```

#### Nota

When more than one image with the same name exists, QEMU finds and uses the most recently built image according to the timestamp.

- This example produces the exact same results as the previous example. This command, however, specifically provides the image and root filesystem type:

```
$ runqemu qemux86-64 core-image-minimal ext4
```

- This example starts QEMU in a temporary root filesystem ("snapshot") with no graphical environment ("nographic"), meaning QEMU is started in the current shell:

```
$ runqemu qemux86-64 snapshot nographic
```

Running in "snapshot" mode means that changes in root filesystem will not remain after quitting QEMU.

- This example specifies to boot an [Initramfs](#) image and to enable audio in QEMU. For this case, `runqemu` sets the internal variable `FSTYPE` to `cpio.gz`. Also, for audio to be enabled, an appropriate driver must be installed (see the `audio` option in [runqemu Command-Line Options](#) for more information):

```
$ runqemu qemux86-64 ramfs audio
```

- This example does not provide enough information for QEMU to launch. While the command does provide a root filesystem type, it must also minimally provide a `MACHINE`, `KERNEL`, or `VM` option:

```
$ runqemu ext4
```

- This example specifies to boot a virtual machine image (`.wic.vmdk` file). From the `.wic.vmdk`, `runqemu` determines the QEMU architecture (`MACHINE`) to be "qemux86-64" and the root filesystem type to be "vmdk":

```
$ runqemu /home/scott-lenovo/vm/core-image-minimal-qemux86-64.wic.vmdk
```

### 8.40.3 Switching Between Consoles

When booting or running QEMU, you can switch between supported consoles by using Ctrl+Alt+number. For example, Ctrl+Alt+3 switches you to the serial console as long as that console is enabled. Being able to switch consoles is helpful, for example, if the main QEMU console breaks for some reason.

#### Nota

Usually, "2" gets you to the main console and "3" gets you to the serial console.

### 8.40.4 Removing the Splash Screen

You can remove the splash screen when QEMU is booting by using Alt+left. Removing the splash screen allows you to see what is happening in the background.

### 8.40.5 Disabling the Cursor Grab

The default QEMU integration captures the cursor within the main window. It does this since standard mouse devices only provide relative input and not absolute coordinates. You then have to break out of the grab using the "Ctrl+Alt" key combination. However, the Yocto Project's integration of QEMU enables the wacom USB touch pad driver by default to allow input of absolute coordinates. This default means that the mouse can enter and leave the main window without the grab taking effect leading to a better user experience.

### 8.40.6 Running Under a Network File System (NFS) Server

One method for running QEMU is to run it on an NFS server. This is useful when you need to access the same file system from both the build and the emulated system at the same time. It is also worth noting that the system does not need root privileges to run. It uses a user space NFS server to avoid that. Follow these steps to set up for running QEMU using an NFS server.

1. *Extract a Root Filesystem:* Once you are able to run QEMU in your environment, you can use the `runqemu-extract-sdk` script, which is located in the `scripts` directory along with the `runqemu` script.

The `runqemu-extract-sdk` takes a root filesystem tarball and extracts it into a location that you specify. Here is an example that takes a file system and extracts it to a directory named `test-nfs`:

```
runqemu-extract-sdk ./tmp/deploy/images/qemux86-64/core-image-sato-qemux86-64.  
→tar.bz2 test-nfs
```

2. *Start QEMU:* Once you have extracted the file system, you can run `runqemu` normally with the additional location of the file system. You can then also make changes to the files within `./test-nfs` and see those changes appear in the image in real time. Here is an example using the `qemux86` image:

```
runqemu qemux86-64 ./test-nfs
```



**i Nota**

Should you need to start, stop, or restart the NFS share, you can use the following commands:

- To start the NFS share:

```
runqemu-export-rootfs start file-system-location
```

- To stop the NFS share:

```
runqemu-export-rootfs stop file-system-location
```

- To restart the NFS share:

```
runqemu-export-rootfs restart file-system-location
```

### 8.40.7 QEMU CPU Compatibility Under KVM

By default, the QEMU build compiles for and targets 64-bit and x86 Intel Core2 Duo processors and 32-bit x86 Intel Pentium II processors. QEMU builds for and targets these CPU types because they display a broad range of CPU feature compatibility with many commonly used CPUs.

Despite this broad range of compatibility, the CPUs could support a feature that your host CPU does not support. Although this situation is not a problem when QEMU uses software emulation of the feature, it can be a problem when QEMU is running with KVM enabled. Specifically, software compiled with a certain CPU feature crashes when run on a CPU under KVM that does not support that feature. To work around this problem, you can override QEMU's runtime CPU setting by changing the `QB_CPU_KVM` variable in `qemuboot.conf` in the [Build Directory](#) `deploy/image` directory. This setting specifies a `-cpu` option passed into QEMU in the `runqemu` script. Running `qemu -cpu help` returns a list of available supported CPU types.

### 8.40.8 QEMU Performance

Using QEMU to emulate your hardware can result in speed issues depending on the target and host architecture mix. For example, using the `qemux86` image in the emulator on an Intel-based 32-bit (x86) host machine is fast because the target and host architectures match. On the other hand, using the `qemuarm` image on the same Intel-based host can be slower. But, you still achieve faithful emulation of ARM-specific issues.

To speed things up, the QEMU images support using `distcc` to call a cross-compiler outside the emulated system. If you used `runqemu` to start QEMU, and the `distccd` application is present on the host system, any BitBake cross-compiling toolchain available from the build system is automatically used from within QEMU simply by calling `distcc`. You can accomplish this by defining the cross-compiler variable (e.g. `export CC="distcc"`). Alternatively, if you are using a suitable SDK image or the appropriate stand-alone toolchain is present, the toolchain is also automatically used.

**i Nota**

There are several mechanisms to connect to the system running on the QEMU emulator:

- QEMU provides a framebuffer interface that makes standard consoles available.

- Generally, headless embedded devices have a serial port. If so, you can configure the operating system of the running image to use that port to run a console. The connection uses standard IP networking.
- SSH servers are available in some QEMU images. The `core-image-sato` QEMU image has a Dropbear secure shell (SSH) server that runs with the root password disabled. The `core-image-full-cmdline` QEMU image has OpenSSH instead of Dropbear. Including these SSH servers allow you to use standard `ssh` and `scp` commands. The `core-image-minimal` QEMU image, however, contains no SSH server.
- You can use a provided, user-space NFS server to boot the QEMU session using a local copy of the root filesystem on the host. In order to make this connection, you must extract a root filesystem tarball by using the `runqemu-extract-sdk` command. After running the command, you must then point the `runqemu` script to the extracted directory instead of a root filesystem image file. See the "[Running Under a Network File System \(NFS\) Server](#)" section for more information.

### 8.40.9 QEMU Command-Line Syntax

The basic `runqemu` command syntax is as follows:

```
$ runqemu [option ] [...]
```

Based on what you provide on the command line, `runqemu` does a good job of figuring out what you are trying to do. For example, by default, QEMU looks for the most recently built image according to the timestamp when it needs to look for an image. Minimally, through the use of options, you must provide either a machine name, a virtual machine image (`*wic.vmdk`), or a kernel image (`*.bin`).

Here is the command-line help output for the `runqemu` command:

```
$ runqemu --help

Usage: you can run this script with any valid combination
of the following environment variables (in any order):
  KERNEL - the kernel image file to use
  ROOTFS - the rootfs image file or nfsroot directory to use
  MACHINE - the machine name (optional, autodetected from KERNEL filename if
↳ unspecified)
Simplified QEMU command-line options can be passed with:
  nographic - disable video console
  serial - enable a serial console on /dev/ttyS0
  slirp - enable user networking, no root privileges required
  kvm - enable KVM when running x86/x86_64 (VT-capable CPU required)
  kvm-vhost - enable KVM with vhost when running x86/x86_64 (VT-capable CPU
↳ required)
  publicvnc - enable a VNC server open to all hosts
  audio - enable audio
  [*/]ovmf* - OVMF firmware file or base name for booting with UEFI
  tcpserial=<port> - specify tcp serial port number
```

(continues on next page)

(continua dalla pagina precedente)

```

biosdir=<dir> - specify custom bios dir
biosfilename=<filename> - specify bios filename
qemuparams=<xyz> - specify custom parameters to QEMU
bootparams=<xyz> - specify custom kernel parameters during boot
help, -h, --help: print this text

```

**Examples:**

```

runqemu
runqemu qemuarm
runqemu tmp/deploy/images/qemuarm
runqemu tmp/deploy/images/qemux86/<qemuboot.conf>
runqemu qemux86-64 core-image-sato ext4
runqemu qemux86-64 wic-image-minimal wic
runqemu path/to/bzImage-qemux86.bin path/to/nfsrootdir/ serial
runqemu qemux86 iso/hddimg/wic.vmdk/wic.qcow2/wic.vdi/ramfs/cpio.gz...
runqemu qemux86 qemuparams="-m 256"
runqemu qemux86 bootparams="psplash=false"
runqemu path/to/<image>-<machine>.wic
runqemu path/to/<image>-<machine>.wic.vmdk

```

### 8.40.10 runqemu Command-Line Options

Here is a description of `runqemu` options you can provide on the command line:

** Nota**

If you do provide some "illegal" option combination or perhaps you do not provide enough in the way of options, `runqemu` provides appropriate error messaging to help you correct the problem.

- **QEMUARCH**: The QEMU machine architecture, which must be "qemuarm", "qemuarm64", "qemumips", "qemumips64", "qemuppc", "qemux86", or "qemux86-64".
- **VM**: The virtual machine image, which must be a `.wic.vmdk` file. Use this option when you want to boot a `.wic.vmdk` image.
- **ROOTFS**: A root filesystem that has one of the following filetype extensions: "ext2", "ext3", "ext4", "jffs2", "nfs", or "btrfs". If the filename you provide for this option uses "nfs", it must provide an explicit root filesystem path.
- **KERNEL**: A kernel image, which is a `.bin` file. When you provide a `.bin` file, `runqemu` detects it and assumes the file is a kernel image.
- **MACHINE**: The architecture of the QEMU machine, which must be one of the following: "qemux86", "qemux86-64", "qemuarm", "qemuarm64", "qemumips", "qemumips64", or "qemuppc". The MACHINE and QEMUARCH options are basically identical. If you do not provide a MACHINE option, `runqemu` tries to determine it based on other options.

- `ramfs`: Indicates you are booting an *Initramfs* image, which means the `FSTYPE` is `cpio.gz`.
- `iso`: Indicates you are booting an ISO image, which means the `FSTYPE` is `.iso`.
- `nographic`: Disables the video console, which sets the console to "ttyS0". This option is useful when you have logged into a server and you do not want to disable forwarding from the X Window System (X11) to your workstation or laptop.
- `serial`: Enables a serial console on `/dev/ttyS0`.
- `biosdir`: Establishes a custom directory for BIOS, VGA BIOS and keymaps.
- `biosfilename`: Establishes a custom BIOS name.
- `qemuparams="\xyz\"`: Specifies custom QEMU parameters. Use this option to pass options other than the simple "kvm" and "serial" options.
- `bootparams="\xyz\"`: Specifies custom boot parameters for the kernel.
- `audio`: Enables audio in QEMU. The `MACHINE` option must be either "qemux86" or "qemux86-64" in order for audio to be enabled. Additionally, the `snd_intel8x0` or `snd_ens1370` driver must be installed in linux guest.
- `slirp`: Enables "slirp" networking, which is a different way of networking that does not need root access but also is not as easy to use or comprehensive as the default.

Using `slirp` by default will forward the guest machine's 22 and 23 TCP ports to host machine's 2222 and 2323 ports (or the next free ports). Specific forwarding rules can be configured by setting `QB_SLIRP_OPT` as environment variable or in `qemuboot.conf` in the *Build Directory* `deploy/image` directory. Examples:

```
QB_SLIRP_OPT = "-netdev user,id=net0,hostfwd=tcp::8080-:80"

QB_SLIRP_OPT = "-netdev user,id=net0,hostfwd=tcp::8080-:80,hostfwd=tcp::2222-↔:22"
```

The first example forwards TCP port 80 from the emulated system to port 8080 (or the next free port) on the host system, allowing access to an http server running in QEMU from `http://<host ip>:8080/`.

The second example does the same, but also forwards TCP port 22 on the guest system to 2222 (or the next free port) on the host system, allowing ssh access to the emulated system using `ssh -P 2222 <user>@<host ip>`.

Keep in mind that proper configuration of firewall software is required.

- `kvm`: Enables KVM when running "qemux86" or "qemux86-64" QEMU architectures. For KVM to work, all the following conditions must be met:
  - Your `MACHINE` must be either `qemux86` or `qemux86-64`.
  - Your build host has to have the KVM modules installed, which are `/dev/kvm`.
  - The build host `/dev/kvm` directory has to be both writable and readable.
- `kvm-vhost`: Enables KVM with `VHOST` support when running "qemux86" or "qemux86-64" QEMU architectures. For KVM with `VHOST` to work, the following conditions must be met:

- `kvm` option conditions defined above must be met.
  - Your build host has to have virtio net device, which are `/dev/vhost-net`.
  - The build host `/dev/vhost-net` directory has to be either readable or writable and "slirp-enabled".
- `publicvnc`: Enables a VNC server open to all hosts.

## 8.41 Locking and Unlocking Recipes Using `bblock`

By design, the OpenEmbedded build system builds everything from scratch unless BitBake determines that specific tasks do not require rebuilding. At startup, it computes a signature for all tasks, based on the task's input. Then, it compares these signatures with the ones from the sstate cache (if they exist). Any changes cause the task to rerun.

During development, changes might trigger BitBake to rebuild certain recipes, even when we know they do not require rebuilding at that stage. For example, modifying a recipe can lead to rebuilding its native counterpart, which might prove unnecessary. Editing the `python3` recipe, for instance, can prompt BitBake to rebuild `python3-native` along with any recipes that depend on it.

To prevent this, use `bblock` to lock specific tasks or recipes to specific signatures, forcing BitBake to use the sstate cache for them.

### Avvertimento

Use `bblock` only during the development phase.

Forcing BitBake to use the sstate cache, regardless of input changes, means the recipe metadata no longer directly reflect the output. Use this feature with caution. If you do not understand why signatures change, see the section on [understanding what changed](#).

### 8.41.1 Locking tasks and recipes

To lock a recipe, use:

```
$ bblock recipe
```

You can also use a space-separated list of recipes to lock multiple recipes:

```
$ bblock recipe1 recipe2
```

Locking a recipe means locking all tasks of the recipe. If you need to lock only particular tasks, use the `-t` option with a comma-separated list of tasks:

```
$ bblock -t task1,task2 recipe
```

## 8.41.2 Unlocking tasks and recipes

To unlock a recipe, use the `-r` option:

```
$ bblock -r recipe
```

You can also use a space-separated list of recipes to unlock multiple recipes:

```
$ bblock -r recipe1 recipe2
```

Unlocking a recipe means unlocking all tasks of the recipe. If you need to unlock only particular tasks use the `-t` option with a comma-separated list of tasks:

```
$ bblock -r -t task1,task2 recipe
```

To unlock all recipes, do not specify any recipe:

```
$ bblock -r
```

## 8.41.3 Configuration file

`bblock` will dump the signatures in the `build/conf/bblock.conf` file, included by default in `meta/conf/bitbake.conf`.

To dump the file, use the `-d` option:

```
$ bblock -d
```

## 8.41.4 Locking mechanism

`bblock` computes the signature(s) of the task(s) and sets the 3 following variables: `SIGGEN_LOCKEDSIGS`, `SIGGEN_LOCKEDSIGS_TYPES` and `SIGGEN_LOCKEDSIGS_TASKSIG_CHECK`.

In particular, `bblock` sets:

```
SIGGEN_LOCKEDSIGS_TASKSIG_CHECK = "info"
SIGGEN_LOCKEDSIGS_TYPES += "${PACKAGE_ARCHS}"

SIGGEN_LOCKEDSIGS_<package_arch> += "<recipe>:<task>:<signature>"
```

This produces architecture specific locks and reminds user that some tasks have locked signatures.

## 8.41.5 Example

When working on the `python3` recipe, we can lock `python3-native` with the following:

```
$ bblock python3-native
$ bblock -d
# Generated by bblock
SIGGEN_LOCKEDSIGS_TASKSIG_CHECK = "info"
```

(continues on next page)

(continua dalla pagina precedente)

```

SIGGEN_LOCKEDSIGSIGS_TYPES += "${PACKAGE_ARCHS}"

SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_
↳patch:865859c27e603ba42025b7bb766c3cd4c0f477e4962cfd39128c0619d695fce7"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_populate_
↳sysroot:f8fa5d3194cef638416000252b959e86d0a19f6b7898e1f56b643c588cdd8605"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_prepare_recipe_
↳sysroot:fe295ac505d9d1143313424b201c6f3f2a0a90da40a13a905b86b874705f226a"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_
↳fetch:1b6e4728fee631bc7a8a7006855c5b8182a8224579e32e3d0a2db77c26459f25"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_
↳unpack:2ad74d6f865ef75c35c0e6bbe3f9a90923a6b2c62c18a3ddef514ea31fbc588f"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_deploy_source_date_
↳epoch:15f89b8483c1ad7507480f337619bb98c26e231227785eb3543db163593e7b42"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_
↳configure:7960c13d23270fdb12b3a7c426ce1da0d2f5c7cf5e5d3f5bdce5fa330eb7d482"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_
↳compile:012e1d4a63f1a78fc2143bd90d704dbcf5865c5257d6272aa7540ec1cd3063d9"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_
↳install:d3401cc2afa4c996beb154beaad3e45fa0272b9c56fb86e9db14ec3544c68f9d"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_
↳build:fa88bb7afb9046c0417c24a3fa98a058653805a8b00eda2c2d7fea68fc42f882"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_collect_spdx_
↳deps:cc9c53ba7c495567e9a38ec4801830c425c0d1f895aa2fc66930a2edd510d9b4"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_create_
↳spdx:766a1d09368438b7b5a1a8e2a8f823b2b731db44b57e67d8b3196de91966f9c5"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_create_package_
↳spdx:46f80faeab25575e9977ba3bf14c819489c3d489432ae5145255635108c21020"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_recipe_
↳qa:cb960cdb074e7944e894958db58f3dc2a0436ecf87c247feb3e095e214fec0e4"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_populate_
↳lic:15657441621ee83f15c2e650e7edbb036870b56f55e72e046c6142da3c5783fd"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_create_
↳manifest:24f0abbec221d27bbb2909b6e846288b12cab419f1faf9f5006ed80423d37e28"
SIGGEN_LOCKEDSIGSIGS_x86_64 += "python3-native:do_addto_recipe_
↳sysroot:bc6a1905f113128de3f88d702b706befd6a786267c045ee82532759a7c214d7"

```

## 8.42 Setting up a Shared State Cache Mirror

This document explains how to set up a server that hosts shared state artifacts that can be reused by machines connecting to the server.


The concept of "shared state" is explained in the *Task Setscene e Shared State* section of the Yocto Project Overview and Concepts Manual. These artifacts are files that are by default placed in the shared state directory (*SSTATE\_DIR*).

This document explains how to share the content of this directory through the use of the `SSTATE_MIRRORS` variable.

### 8.42.1 Use-case

The most common use-case for setting up a shared state cache mirror is usually when there is a dedicated machine in an infrastructure building images at a regular interval, thus populating a shared state cache directory frequently. Usually, this machine is part of a **CI/CD** type of environment.

Since the shared state directory of this machine contains most of the items needed to accelerate a new build, it can be interesting to share it to remote clients connecting to the machine and fetching the artifacts over the network:



With this kind of setup, it is assumed that:

- Clients connect to the server over some protocol such as HTTP. In practice, the protocol should be one supported by BitBake (see [the supported fetchers](#)).
- The shared state directory (*SSTATE\_DIR*) of the build machine is read-only from the point of view of the clients.
- The previous points also means that clients hold their own copy of the shared state artifacts in their own shared state directory.

### 8.42.2 Server Setup

There are many ways of setting up a file hosting server. To illustrate, this document will use a basic HTTP server started thanks to the `http.server` Python module.

On our build machine, we assume that the server shares the shared state from the *Build Directory*:

```
build/
├─ ...
├─ sstate-cache/
└─ ...
```



With the `http.server` Python module, the server can be started as follows:

```
$ python3 -m http.server -d ../build/sstate-cache
Serving HTTP on 0.0.0.0 port 8000 (http://0.0.0.0:8000/) ...
```

### 8.42.3 Client Configuration

Configuring clients to this server happens through a *configuration file*, for example, the *site.conf* file. Only the *SSTATE\_MIRRORS* variable is needed to setup the connection:

```
SSTATE_MIRRORS = "file://.* http://127.0.0.1:8000/PATH;downloadfilename=PATH"
```

The line above depends on your server configuration. Here, the example uses the local `127.0.0.1` IP address (the client is running on the same machine) and the files are served on the port 8000.

With this, the client is configured to download shared state artifacts from the server. This will happen automatically based on the *signatures* of the tasks which are about to run (so only relevant artifacts are fetched).

After running a build, the local shared state directory of the client (configured through its *SSTATE\_DIR* variable), will be populated with the files downloaded from the server.

### 8.42.4 Going Further

- It is recommended to setup a *Equivalenza degli Hash* service on the build machine --- running in parallel of the shared state mirror --- to further speed up builds. See the *Setting up a Hash Equivalence Server* section of the Yocto Project Development Tasks Manual for more information.
- If the mirror is protected behind a username and password, the *build host* needs to be configured so the *build system* is able to download the shared state cache using authentication.

The recommended way to do that is by setting the following parameters in `$HOME/.netrc` (`$HOME` being the *build host* home directory):

```
machine someserver.tld
login <user>
password <password>
```

This file requires permissions set to 400 or 600 to prevent other users from reading the file:

```
$ chmod 600 "$HOME/.netrc"
```

Another method to configure the username and password is from the URL in *SSTATE\_MIRRORS* directly, with the *user* and *pswd* parameters:

```
SSTATE_MIRRORS ?= "\
    file://.* https://someserver.tld/share/sstate/PATH;user=<user>;pswd=
    ↪<password>;downloadfilename=PATH \
"
```

- If the `BB_NO_NETWORK` variable is set to "1" on clients as a means to disable any accesses to the network, the `SSTATE_MIRROR_ALLOW_NETWORK` variable may be used to allow the clients to fetch from the shared state mirror as an exception.
- Multiple shared state sources can be specified in the `SSTATE_MIRRORS` variable. For example:

```
SSTATE_MIRRORS = "\
    file://.* https://someserver.com/PATH;downloadfilename=PATH \
    file://.* https://someotherserver.com/PATH;downloadfilename=PATH \
"
```

The shared state artifacts will be searched on the remote locations in the same order as they are specified in this variable.

- Fetching the shared state artifacts from a local directory, such as an [NFS](#)-mounted directory, is also possible using the `file://` fetcher:

```
SSTATE_MIRRORS = "file://.* file:///path/to/shared-state/PATH;
↪downloadfilename=PATH"
```

- The shared state mirror may be used in combination with GPG signatures to ensure the authenticity of the downloaded files. See the *Firma dello Stato Condiviso* section of the Yocto Project Security Manual for more information.
- The size of the shared state directory on the server may grow over time. The `sstate-cache-management.py` script may be used to remove duplicate files. Otherwise, removing files that have not been accessed for a certain period of time can be done with the standard `find` command, e.g. for removing files older than 2 months:

```
$ find sstate-cache/ -type f -atime +60 -delete
```

## 8.42.5 Troubleshooting

The best way to check that files are being downloaded from the server is probably to check the server logs. For example, using the Python `http.server` module, the following logs are shown:

```
127.0.0.1 - - [20/Jul/2026 14:36:23] "HEAD /d1/75/sstate%3Afile%3Ax86-64-v3-oe-
↪linux%3A5.48%3Ar0%3Ax86-64-v3%3A14
↪%3Ad175b18b8adc9cc3003edfc62f112fd421505bc715d41f36b4d04eef05d226ad_packagedata.
↪tar.zst HTTP/1.1" 200 -
127.0.0.1 - - [20/Jul/2026 14:36:23] "HEAD /f4/11/sstate%3Aos-release%3Aall-oe-
↪linux%3A1.0%3Ar0%3Aallarch%3A14
↪%3Af411b2f27319283694ab13bf0d8965a7dd26428431418dfb7505f3d1cdd0dbfd_package_
↪write_ipk.tar.zst HTTP/1.1" 404 -
```

Some artifacts may be found (returning 200 above). Some others will not be found because the expected artifacts on the client is not present on the server, in which case the client will rebuild the task (and its dependencies).

## 8.43 Setting up a Hash Equivalence Server

A *Equivalenza degli Hash* server can help reduce build times by using the mechanism described in the *Equivalenza degli Hash* section of the Yocto Project Overview and Concepts Manual.

This document will guide you through the steps required to set up the reference Hash Equivalence server provided by the `bitbake-hashserv` script in *BitBake*.

This guide will explain how to set up a local Hash Equivalence server and does not explain how to set up the surrounding infrastructure to secure this server.

### 8.43.1 Hash Equivalence Server Setup

From this point onwards, the commands displayed below are assumed to be run from the *BitBake* repository, which can be found [here](#).

To start a basic Hash Equivalence server, one could simply run:

```
./bin/bitbake-hashserv
```

This will take all of the default options of the script, which are already sufficient to start a local server.

Run `./bin/bitbake-hashserv --help` to see what options the script can take. Some of the important ones are:

- `--database` controls the location of the hash server database (default: `./hashserver.db`).
- `--bind` controls the bind address of the server (default: `unix://./hashserver.sock`).

You can specify three types of addresses:

- `unix://PATH:` will bind to a Unix socket at `PATH`.
- `wss://ADDRESS:PORT:` will bind to a Websocket at `ADDRESS:PORT`.
- `ADDRESS:PORT:` will bind to a raw TCP socket at `ADDRESS:PORT`.
- `--log` can be used to control the logging level of the server (e.g. `INFO` will print information about clients connection to the server).
- `--upstream` can be used to specify an upstream server to pull hashes from. This has no default value, meaning no upstream server is used.
- `--db-username` and `--db-password` can be used to control the access to the database.
- `--read-only` will disable hash reports from clients.

These variables can also be set from the environment from where it is being run. Run `./bin/bitbake-hashserv --help` to get the variable names that you can export.

#### Avvertimento

The shared Hash Equivalence server needs to be maintained together with the *Shared State* cache. Otherwise, the server could report Shared State hashes that only exist on specific clients.

We therefore recommend that one Hash Equivalence server be set up to correspond with a given Shared State cache, and to start this server in *read-only mode* (`--read-only` option), so that it doesn't store equivalences for Shared State caches that are local to clients.

If there is no pre-existing Shared State Cache, the server should allow hashes to be reported (no `--read-only` option) to create the initial Hash Equivalence database.

## 8.43.2 Yocto Project Build Setup

To use the server started in the previous section, set the following variables in a *configuration file*:

```
BB_HASHSERVE = "<bind address>"
BB_SIGNATURE_HANDLER = "OEEquivHash"
```

The `<bind address>` value should be replaced to point to the server started in the previous section.

See the documentation of `BB_SIGNATURE_HANDLER` for more details on this variable.

You can optionally specify an upstream server with `BB_HASHSERVE_UPSTREAM` variable. For example:

```
BB_HASHSERVE_UPSTREAM = "wss://hashserv.yoctoproject.org/ws"
```

This will make the local server pull hashes from the upstream server. The `BB_HASHSERVE_UPSTREAM` only works when a server is running (`BB_HASHSERVE` is set).

To output debugging information on what is happening with Hash Equivalence when builds are started, you can configure *BitBake* logging as follows from a *configuration file*:

```
BB_LOGCONFIG = "hashequiv.json"
```

With `hashequiv.json` containing the following content:

```
{
  "version": 1,
  "loggers": {
    "BitBake.SigGen.HashEquiv": {
      "level": "VERBOSE",
      "handlers": ["BitBake.verbconsole"]
    },
    "BitBake.RunQueue.HashEquiv": {
      "level": "VERBOSE",
      "handlers": ["BitBake.verbconsole"]
    }
  }
}
```

This will make Hash Equivalence related changes be printed on the console, such as:

```
NOTE: Task <recipe.bb>:do_<task> unihash changed to ↵  
↵dc0da29c62a2d78d8d853fbb9c173778fe7d6fa4a68c67494b17afffe8ca1894
```

The Yocto Project ®

[<docs@lists.yoctoproject.org>](mailto:docs@lists.yoctoproject.org)

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.



---

## Manuale di Sviluppo del Kernel Linux di Yocto Project

---

### 9.1 Introduzione

#### 9.1.1 Overview

Regardless of how you intend to make use of the Yocto Project, chances are you will work with the Linux kernel. This manual covers the following:

- how to set up your build host to support kernel development
- coverage of the kernel development process
- background information on the Yocto Linux kernel *Metadata*
- common tasks you can perform using the kernel tools
- how to use the kernel Metadata needed to work with the kernel inside the Yocto Project
- details on how the Yocto Project team develops and maintains Yocto Linux kernel Git repositories and Metadata.

Each Yocto Project release has a set of Yocto Linux kernel recipes, whose Git repositories you can view in the Yocto [Source Repositories](#) under the "Yocto Linux Kernel" heading. New recipes for the release track the latest Linux kernel upstream developments from <https://www.kernel.org> and introduce newly-supported platforms. Previous recipes in the release are refreshed and supported for at least one additional Yocto Project release.

Also included is a Yocto Linux kernel development recipe (`linux-yocto-dev.bb`) should you want to work with the very latest in upstream Yocto Linux kernel development and kernel Metadata development.

**i Nota**

For more on Yocto Linux kernels, see the "*Yocto Project Kernel Development and Maintenance*" section.

The Yocto Project also provides a powerful set of kernel tools for managing Yocto Linux kernel sources and configuration data. You can use these tools to make a single configuration change, apply multiple patches, or work with your own kernel sources.

In particular, the kernel tools allow you to generate configuration fragments that specify only what you must, and nothing more. Configuration fragments only need to contain the highest level visible `CONFIG` options as presented by the Yocto Linux kernel `menuconfig` system. Contrast this against a complete Yocto Linux kernel `.config` file, which includes all the automatically selected `CONFIG` options. This efficiency reduces your maintenance effort and allows you to further separate your configuration in ways that make sense for your project. A common split separates policy and hardware. For example, all your kernels might support the `proc` and `sys` filesystems, but only specific boards require sound, USB, or specific drivers. Specifying these configurations individually allows you to aggregate them together as needed, but maintains them in only one place. Similar logic applies to separating source changes.

If you do not maintain your own kernel sources and need to make only minimal changes to the sources, the released recipes provide a vetted base upon which to layer your changes. Doing so allows you to benefit from the continual kernel integration and testing performed during development of the Yocto Project.

If, instead, you have a very specific Linux kernel source tree and are unable to align with one of the official Yocto Linux kernel recipes, you have a way to use the Yocto Project Linux kernel tools with your own kernel sources.

The remainder of this manual provides instructions for completing specific Linux kernel development tasks. These instructions assume you are comfortable working with [BitBake](#) recipes and basic open-source development tools. Understanding these concepts will facilitate the process of working with the kernel recipes. If you find you need some additional background, please be sure to review and understand the following documentation:


- *Build Rapida di un'Immagine con lo Yocto Project* document.
- *Manuale Introduttivo e Concetti di Yocto Project*.
- *devtool workflow* as described in the Yocto Project Application Development and the Extensible Software Development Kit (eSDK) manual.
- The "*Comprendere e Creare i Layer*" section in the Yocto Project Development Tasks Manual.
- The "*Kernel Modification Workflow*" section.

## 9.1.2 Kernel Modification Workflow

Kernel modification involves changing the Yocto Project kernel, which could involve changing configuration options as well as adding new kernel recipes. Configuration changes can be added in the form of configuration fragments, while recipe modification comes through the kernel's `recipes-kernel` area in a kernel layer you create.

This section presents a high-level overview of the Yocto Project kernel modification workflow. The illustration and accompanying list provide general information and references for further information.





1. *Set up Your Host Development System to Support Development Using the Yocto Project:* See the "[Setting Up to Use the Yocto Project](#)" section in the Yocto Project Development Tasks Manual for options on how to get a build host ready to use the Yocto Project.

2. *Set Up Your Host Development System for Kernel Development:* It is recommended that you use `devtool` for kernel development. Alternatively, you can use traditional kernel development methods with the Yocto Project. Either way, there are steps you need to take to get the development environment ready.

Using `devtool` requires that you have a clean build of the image. For more information, see the "[Getting Ready to Develop Using devtool](#)" section.

Using traditional kernel development requires that you have the kernel source available in an isolated local Git repository. For more information, see the "[Getting Ready for Traditional Kernel Development](#)" section.

3. *Make Changes to the Kernel Source Code if applicable:* Modifying the kernel does not always mean directly changing source files. However, if you have to do this, you make the changes to the files in the Yocto's [Build Directory](#) if you are using `devtool`. For more information, see the "[Using devtool to Patch the Kernel](#)" section.

If you are using traditional kernel development, you edit the source files in the kernel's local Git repository. For more information, see the "[Using Traditional Kernel Development to Patch the Kernel](#)" section.

4. *Make Kernel Configuration Changes if Applicable:* If your situation calls for changing the kernel's configuration, you can use `menuconfig`, which allows you to interactively develop and test the configuration changes you are making to the kernel. Saving changes you make with `menuconfig` updates the kernel's `.config` file.

**i Nota**

Try to resist the temptation to directly edit an existing `.config` file, which is found in the *Build Directory* among the source code used for the build. Doing so, can produce unexpected results when the OpenEmbedded build system regenerates the configuration file.

Once you are satisfied with the configuration changes made using `menuconfig` and you have saved them, you can directly compare the resulting `.config` file against an existing original and gather those changes into a *configuration fragment file* to be referenced from within the kernel's `.bbappend` file.

Additionally, if you are working in a BSP layer and need to modify the BSP's kernel's configuration, you can use `menuconfig`.

5. *Rebuild the Kernel Image With Your Changes*: Rebuilding the kernel image applies your changes. Depending on your target hardware, you can verify your changes on actual hardware or perhaps QEMU.

The remainder of this developer's guide covers common tasks typically used during kernel development, advanced Metadata usage, and Yocto Linux kernel maintenance concepts.

## 9.2 Common Tasks

This chapter presents several common tasks you perform when you work with the Yocto Project Linux kernel. These tasks include preparing your host development system for kernel development, preparing a layer, modifying an existing recipe, patching the kernel, configuring the kernel, iterative development, working with your own sources, and incorporating out-of-tree modules.

**i Nota**

The examples presented in this chapter work with the Yocto Project 2.4 Release and forward.

### 9.2.1 Preparazione dell'Host di Build per Lavorare sul Kernel.

Before you can do any kernel development, you need to be sure your build host is set up to use the Yocto Project. For information on how to get set up, see the "*Setting Up to Use the Yocto Project*" section in the Yocto Project Development Tasks Manual.

**i Nota**

Be sure you check out the appropriate development branch or you create your local branch by checking out a specific tag to get the desired version of Yocto Project.

Kernel development is best accomplished using *devtool* and not through traditional kernel workflow methods. The remainder of this section provides information for both scenarios.

**Getting Ready to Develop Using devtool**

Follow these steps to prepare to update the kernel image using *devtool*. Completing this procedure leaves you with a clean kernel image and ready to make modifications as described in the "*Using devtool to Patch the Kernel*" section:

1. *Initialize the Build Environment:* Follow the *Setting Up to Use the Yocto Project* section of the Yocto Project Development Tasks Manual in order to have a ready-to-use shell that can execute *devtool*.
2. *Prepare Your local.conf File:* By default, the *MACHINE* variable is set to "qemux86-64", which is fine if you are building for the QEMU emulator in 64-bit mode. However, if you are not, you need to set the *MACHINE* variable appropriately in your *build/conf/local.conf* file found in the *Build Directory* (i.e. *bitbake-builds/build* in this example).

Also, since you are preparing to work on the kernel image, you need to set the *MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS* variable to include kernel modules.

In this example we wish to build for qemux86 so we must set the *MACHINE* variable to "qemux86" and also add the "kernel-modules". As described we do this by appending to *build/conf/local.conf*:

```
MACHINE = "qemux86"
MACHINE_ESSENTIAL_EXTRA_RRECOMMENDS += "kernel-modules"
```

3. *Create a Layer for Patches:* You need to create a layer to hold patches created for the kernel image. You can use the *bitbake-layers create-layer* command as follows:

```
$ cd bitbake-builds/build
$ bitbake-layers create-layer ../layers/meta-mylayer
NOTE: Starting bitbake server...
Add your new layer with 'bitbake-layers add-layer ../layers/meta-mylayer'
$
```

**i Nota**

For background information on working with common and BSP layers, see the "*Comprendere e Creare i Layer*" section in the Yocto Project Development Tasks Manual and the "*Layer BSP*" section in the Yocto Project Board Support (BSP) Developer's Guide, respectively. For information on how to use the *bitbake-layers create-layer* command to quickly set up a layer, see the "*Creating Your Own Layer*" section in the Yocto Project Development Tasks Manual.

4. *Inform the BitBake Build Environment About Your Layer:* As directed when you created your layer, you need to add the layer to the *BBLAYERS* variable in the *build/conf/bblayers.conf* file as follows:

```
$ cd bitbake-builds/build
$ bitbake-layers add-layer ../../meta-mylayer
NOTE: Starting bitbake server...
$
```

5. *Build the Clean Image:* The final step in preparing to work on the kernel is to build an initial image using bitbake:

```
$ bitbake core-image-minimal
Parsing recipes: 100% |#####| Time:↵
↵0:00:05
Parsing of 830 .bb files complete (0 cached, 830 parsed). 1299 targets, 47↵
↵skipped, 0 masked, 0 errors.
WARNING: No packages to add, building image core-image-minimal unmodified
Loading cache: 100% |#####| Time:↵
↵0:00:00
Loaded 1299 entries from dependency cache.
NOTE: Resolving any missing task queue dependencies
Initializing tasks: 100% |#####| Time:↵
↵0:00:07
Checking sstate mirror object availability: 100% |#####| Time:↵
↵0:00:00
NOTE: Executing SetScene Tasks
NOTE: Executing RunQueue Tasks
NOTE: Tasks Summary: Attempted 2866 tasks of which 2604 didn't need to be↵
↵rerun and all succeeded.
```

If you were building for actual hardware and not for emulation, you could flash the image to a USB stick on */dev/sdd* and boot your device. For an example that uses a Minnowboard, see the [TipsAndTricks/KernelDevelopmentWithEsdk](#) Wiki page.

At this point you have set up to start making modifications to the kernel. For a continued example, see the "[Using devtool to Patch the Kernel](#)" section.

## Getting Ready for Traditional Kernel Development

Getting ready for traditional kernel development using the Yocto Project involves many of the same steps as described in the previous section. However, you need to establish a local copy of the kernel source since you will be editing these files.

Follow these steps to prepare to update the kernel image using traditional kernel development flow with the Yocto Project. Completing this procedure leaves you ready to make modifications to the kernel source as described in the "[Using Traditional Kernel Development to Patch the Kernel](#)" section:

1. *Initialize the BitBake Environment:* Follow the steps in the *Setting Up to Use the Yocto Project* section of the Yocto Project Development Tasks Manual.
2. *Prepare Your local.conf File:* By default, the *MACHINE* variable is set to "qemux86-64", which is fine if you are building for the QEMU emulator in 64-bit mode. However, if you are not, you need to set the *MACHINE* variable appropriately in your *build/conf/local.conf* file found in the *Build Directory* (i.e. bitbake-builds/build in this example).

Also, since you are preparing to work on the kernel image, you need to set the *MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS* variable to include kernel modules.

In this example we wish to build for qemux86 so we must set the *MACHINE* variable to "qemux86" and also add the "kernel-modules". As described we do this by appending to *build/conf/local.conf*:

```
MACHINE = "qemux86"
MACHINE_ESSENTIAL_EXTRA_RRECOMMENDS += "kernel-modules"
```

3. *Create a Layer for Patches:* You need to create a layer to hold patches created for the kernel image. You can use the `bitbake-layers create-layer` command as follows:

```
$ cd bitbake-builds/build
$ bitbake-layers create-layer ../../meta-mylayer
NOTE: Starting bitbake server...
Add your new layer with 'bitbake-layers add-layer ../../meta-mylayer'
```

#### Nota

For background information on working with common and BSP layers, see the "*Comprendere e Creare i Layer*" section in the Yocto Project Development Tasks Manual and the "*Layer BSP*" section in the Yocto Project Board Support (BSP) Developer's Guide, respectively. For information on how to use the `bitbake-layers create-layer` command to quickly set up a layer, see the "*Creating Your Own Layer*" section in the Yocto Project Development Tasks Manual.

4. *Inform the BitBake Build Environment About Your Layer:* As directed when you created your layer, you need to add the layer to the *BBLAYERS* variable in the *build/conf/bblayers.conf* file as follows:

```
$ cd bitbake-builds/build
$ bitbake-layers add-layer ../../meta-mylayer
NOTE: Starting bitbake server ...
$
```

5. *Create a Local Copy of the Kernel Git Repository:* You can find Git repositories of supported Yocto Project kernels organized under "Yocto Linux Kernel" in the Yocto Project Source Repositories at <https://git.yoctoproject.org/>.

For simplicity, it is recommended that you create your copy of the kernel Git repository outside of the *Source Directory*. Also, be sure you are in the `standard/base` branch.

The following commands show how to create a local copy of the `linux-yocto-4.12` kernel and be in the `standard/base` branch:

```
$ cd ~
$ git clone https://git.yoctoproject.org/linux-yocto-4.12 --branch standard/
→base
Cloning into 'linux-yocto-4.12'...
remote: Counting objects: 6097195, done.
remote: Compressing objects: 100% (901026/901026), done.
remote: Total 6097195 (delta 5152604), reused 6096847 (delta 5152256)
Receiving objects: 100% (6097195/6097195), 1.24 GiB | 7.81 MiB/s, done.
Resolving deltas: 100% (5152604/5152604), done. Checking connectivity... done.
Checking out files: 100% (59846/59846), done.
```

#### Nota

The `linux-yocto-4.12` kernel can be used with the Yocto Project 2.4 release and forward. You cannot use the `linux-yocto-4.12` kernel with releases prior to Yocto Project 2.4.

6. *Create a Local Copy of the Kernel Cache Git Repository:* For simplicity, it is recommended that you create your copy of the kernel cache Git repository outside of the *Source Directory*. Also, for this example, be sure you are in the `yocto-4.12` branch.

The following commands show how to create a local copy of the `yocto-kernel-cache` and switch to the `yocto-4.12` branch:

```
$ cd ~
$ git clone https://git.yoctoproject.org/yocto-kernel-cache --branch yocto-4.12
Cloning into 'yocto-kernel-cache'...
remote: Counting objects: 22639, done.
remote: Compressing objects: 100% (9761/9761), done.
remote: Total 22639 (delta 12400), reused 22586 (delta 12347)
Receiving objects: 100% (22639/22639), 22.34 MiB | 6.27 MiB/s, done.
Resolving deltas: 100% (12400/12400), done.
Checking connectivity... done.
```

At this point, you are ready to start making modifications to the kernel using traditional kernel development steps. For a continued example, see the "*Using Traditional Kernel Development to Patch the Kernel*" section.

## 9.2.2 Creating and Preparing a Layer

If you are going to be modifying kernel recipes, it is recommended that you create and prepare your own layer in which to do your work. Your layer contains its own *BitBake* append files (`.bbappend`) and provides a convenient mechanism to create your own recipe files (`.bb`) as well as store and use kernel patch files. For background information on working with layers, see the "*Comprendere e Creare i Layer*" section in the Yocto Project Development Tasks Manual.

**i Nota**

The Yocto Project comes with many tools that simplify tasks you need to perform. One such tool is the `bit-bake-layers create-layer` command, which simplifies creating a new layer. See the "[Creating Your Own Layer](#)" section in the Yocto Project Development Tasks Manual for information on how to use this script to quick set up a new layer.

To better understand the layer you create for kernel development, the following section describes how to create a layer without the aid of tools. These steps assume creation of a layer named `mylayer` in your home directory:

1. *Create Structure:* Create the layer's structure:

```
$ mkdir -p meta-mylayer/conf meta-mylayer/recipes-kernel/linux/linux-yocto
```

The `conf` directory holds your configuration files, while the `recipes-kernel` directory holds your append file and eventual patch files.

2. *Create the Layer Configuration File:* Move to the `meta-mylayer/conf` directory and create the `layer.conf` file as follows:

```
# We have a conf and classes directory, add to BBPATH
BBPATH .= ":${LAYERDIR}"

# We have recipes-* directories, add to BBFILES
BBFILES += "${LAYERDIR}/recipes-*/*/*.bb \
           ${LAYERDIR}/recipes-*/*/*.bbappend"

BBFILE_COLLECTIONS += "mylayer"
BBFILE_PATTERN_mylayer = "^${LAYERDIR}/"
BBFILE_PRIORITY_mylayer = "5"
```

Notice `mylayer` as part of the last three statements.

3. *Create the Kernel Recipe Append File:* Move to the `meta-mylayer/recipes-kernel/linux` directory and create the kernel's append file. This example uses the `linux-yocto-4.12` kernel. Thus, the name of the append file is `linux-yocto_4.12.bbappend`:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"

SRC_URI += "file://patch-file-one.patch"
SRC_URI += "file://patch-file-two.patch"
SRC_URI += "file://patch-file-three.patch"
```

The `FILESEXTRAPATHS` and `SRC_URI` statements enable the OpenEmbedded build system to find patch files. For more information on using append files, see the "[Appending Other Layers Metadata With Your Layer](#)" section in the Yocto Project Development Tasks Manual.

## 9.2.3 Modifying an Existing Recipe

In many cases, you can customize an existing linux-yocto recipe to meet the needs of your project. Each release of the Yocto Project provides a few Linux kernel recipes from which you can choose. These are located in *OpenEmbedded-Core (OE-Core)* in `meta/recipes-kernel/linux`.

Modifying an existing recipe can consist of the following:

- *Creating the Append File*
- *Applying Patches*
- *Changing the Configuration*

Before modifying an existing recipe, be sure that you have created a minimal, custom layer from which you can work. See the "*Creating and Preparing a Layer*" section for information.

### Creating the Append File

You create this file in your custom layer. You also name it accordingly based on the linux-yocto recipe you are using. For example, if you are modifying the `meta/recipes-kernel/linux/linux-yocto_6.1.bb` recipe, the append file will typically be located as follows within your custom layer:

```
your-layer/recipes-kernel/linux/linux-yocto_6.1.bbappend
```

The append file should initially extend the *FILESPATH* search path by prepending the directory that contains your files to the *FILESEXTRAPATHS* variable as follows:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"
```

The path `${THISDIR}/${PN}` expands to "linux-yocto" in the current directory for this example. If you add any new files that modify the kernel recipe and you have extended *FILESPATH* as described above, you must place the files in your layer in the following area:

```
your-layer/recipes-kernel/linux/linux-yocto/
```

#### Nota

If you are working on a new machine Board Support Package (BSP), be sure to refer to the *Manuale del Board Support Package (BSP) di Yocto Project*.

As an example, consider the following append file used by the BSPs in `meta-yocto-bsp`:

```
meta-yocto-bsp/recipes-kernel/linux/linux-yocto_6.1.bbappend
```

Here are the contents of this file. Be aware that the actual commit ID strings in this example listing might be different than the actual strings in the file from the `meta-yocto-bsp` layer upstream:



```

KBRANCH:genericx86 = "v6.1/standard/base"
KBRANCH:genericx86-64 = "v6.1/standard/base"
KBRANCH:beaglebone-yocto = "v6.1/standard/beaglebone"

KMACHINE:genericx86 ?= "common-pc"
KMACHINE:genericx86-64 ?= "common-pc-64"
KMACHINE:beaglebone-yocto ?= "beaglebone"

SRCREV_machine:genericx86 ?= "6ec439b4b456ce929c4c07fe457b5d6a4b468e86"
SRCREV_machine:genericx86-64 ?= "6ec439b4b456ce929c4c07fe457b5d6a4b468e86"
SRCREV_machine:beaglebone-yocto ?= "423e1996694b61fbfc8ec3bf062fc6461d64fde1"

COMPATIBLE_MACHINE:genericx86 = "genericx86"
COMPATIBLE_MACHINE:genericx86-64 = "genericx86-64"
COMPATIBLE_MACHINE:beaglebone-yocto = "beaglebone-yocto"

LINUX_VERSION:genericx86 = "6.1.30"
LINUX_VERSION:genericx86-64 = "6.1.30"
LINUX_VERSION:beaglebone-yocto = "6.1.20"

```

This append file contains statements used to support several BSPs that ship with the Yocto Project. The file defines machines using the `COMPATIBLE_MACHINE` variable and uses the `KMACHINE` variable to ensure the machine name used by the OpenEmbedded build system maps to the machine name used by the Linux Yocto kernel. The file also uses the optional `KBRANCH` variable to ensure the build process uses the appropriate kernel branch.

Although this particular example does not use it, the `KERNEL_FEATURES` variable could be used to enable features specific to the kernel. The append file points to specific commits in the *OpenEmbedded-Core (OE-Core)* Git repository branches to identify the exact kernel needed to build the BSP.

One thing missing in this particular BSP, which you will typically need when developing a BSP, is the kernel configuration file (`.config`) for your BSP. When developing a BSP, you probably have a kernel configuration file or a set of kernel configuration files that, when taken together, define the kernel configuration for your BSP. You can accomplish this definition by putting the configurations in a file or a set of files inside a directory located at the same level as your kernel's append file and having the same name as the kernel's main recipe file. With all these conditions met, simply reference those files in the `SRC_URI` statement in the append file.

For example, suppose you had some configuration options in a file called `network_configs.cfg`. You can place that file inside a directory named `linux-yocto` and then add a `SRC_URI` statement such as the following to the append file. When the OpenEmbedded build system builds the kernel, the configuration options are picked up and applied:

```
SRC_URI += "file://network_configs.cfg"
```

To group related configurations into multiple files, you perform a similar procedure. Here is an example that groups separate configurations specifically for Ethernet and graphics into their own files and adds the configurations by using a `SRC_URI` statement like the following in your append file:

```
SRC_URI += "file://myconfig.cfg \  
           file://eth.cfg \  
           file://gfx.cfg"
```

Another variable you can use in your kernel recipe append file is the *FILESEXTRAPATHS* variable. When you use this statement, you are extending the locations used by the OpenEmbedded system to look for files and patches as the recipe is processed.

#### Nota

There are other ways of grouping and defining configuration options. For example, if you are working with a local clone of the kernel repository, you could checkout the kernel's *meta* branch, make your changes, and then push the changes to the local bare clone of the kernel. The result is that you directly add configuration options to the *meta* branch for your BSP. The configuration options will likely end up in that location anyway if the BSP gets added to the Yocto Project.

In general, however, the Yocto Project maintainers take care of moving the *SRC\_URI*-specified configuration options to the kernel's *meta* branch. Not only is it easier for BSP developers not to have to put those configurations in the branch, but having the maintainers do it allows them to apply 'global' knowledge about the kinds of common configuration options multiple BSPs in the tree are typically using. This allows for promotion of common configurations into common features.

## Applying Patches

If you have a single patch or a small series of patches that you want to apply to the Linux kernel source, you can do so just as you would with any other recipe. You first copy the patches to the path added to *FILESEXTRAPATHS* in your *.bbappend* file as described in the previous section, and then reference them in *SRC\_URI* statements.

For example, you can apply a three-patch series by adding the following lines to your linux-yocto *.bbappend* file in your layer:

```
SRC_URI += "file://0001-first-change.patch"  
SRC_URI += "file://0002-second-change.patch"  
SRC_URI += "file://0003-third-change.patch"
```

The next time you run BitBake to build the Linux kernel, BitBake detects the change in the recipe and fetches and applies the patches before building the kernel.

For a detailed example showing how to patch the kernel using *devtool*, see the "*Using devtool to Patch the Kernel*" and "*Using Traditional Kernel Development to Patch the Kernel*" sections.

## Changing the Configuration

You can make wholesale or incremental changes to the final *.config* file used for the eventual Linux kernel configuration by including a *defconfig* file and by specifying configuration fragments in the *SRC\_URI* to be applied to that file.

If you have a complete, working Linux kernel `.config` file you want to use for the configuration, as before, copy that file to the appropriate `${PN}` directory in your layer's `recipes-kernel/linux` directory, and rename the copied file to `defconfig`. Then, add the following lines to the `linux-yocto .bbappend` file in your layer:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"
SRC_URI += "file://defconfig"
```

The `SRC_URI` tells the build system how to search for the file, while the `FILESEXTRAPATHS` extends the `FILESPATH` variable (search directories) to include the `${PN}` directory you created to hold the configuration changes.

You can also use a regular `defconfig` file, as generated by the `do_savedefconfig` task instead of a complete `.config` file. This only specifies the non-default configuration values. You need to additionally set `KCONFIG_MODE` in the `linux-yocto .bbappend` file in your layer:

```
KCONFIG_MODE = "alldefconfig"
```

### Nota

The build system applies the configurations from the `defconfig` file before applying any subsequent configuration fragments. The final kernel configuration is a combination of the configurations in the `defconfig` file and any configuration fragments you provide. You need to realize that if you have any configuration fragments, the build system applies these on top of and after applying the existing `defconfig` file configurations.

Generally speaking, the preferred approach is to determine the incremental change you want to make and add that as a configuration fragment. For example, if you want to add support for a basic serial console, create a file named `8250.cfg` in the `${PN}` directory with the following content (without indentation):

```
CONFIG_SERIAL_8250=y
CONFIG_SERIAL_8250_CONSOLE=y
CONFIG_SERIAL_8250_PCI=y
CONFIG_SERIAL_8250_NR_UARTS=4
CONFIG_SERIAL_8250_RUNTIME_UARTS=4
CONFIG_SERIAL_CORE=y
CONFIG_SERIAL_CORE_CONSOLE=y
```

Next, include this configuration fragment and extend the `FILESPATH` variable in your `.bbappend` file:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"
SRC_URI += "file://8250.cfg"
```

The next time you run BitBake to build the Linux kernel, BitBake detects the change in the recipe and fetches and applies the new configuration before building the kernel.

For a detailed example showing how to configure the kernel, see the "[Configuring the Kernel](#)" section.

## Using an "In-Tree" `defconfig` File

It might be desirable to have kernel configuration fragment support through a `defconfig` file that is pulled from the kernel source tree for the configured machine. By default, the OpenEmbedded build system looks for `defconfig` files in the layer used for Metadata, which is "out-of-tree", and then configures them using the following:

```
SRC_URI += "file://defconfig"
```

If you do not want to maintain copies of `defconfig` files in your layer but would rather allow users to use the default configuration from the kernel tree and still be able to add configuration fragments to the `SRC_URI` through, for example, append files, you can direct the OpenEmbedded build system to use a `defconfig` file that is "in-tree".

To specify an "in-tree" `defconfig` file, use the following statement form:

```
KBUILD_DEFCONFIG:<machine> ?= "defconfig_file"
```

Here is an example that assigns the `KBUILD_DEFCONFIG` variable utilizing an override for the "raspberrypi2" *MACHINE* and provides the path to the "in-tree" `defconfig` file to be used for a Raspberry Pi 2, which is based on the Broadcom 2708/2709 chipset:

```
KBUILD_DEFCONFIG:raspberrypi2 ?= "bcm2709_defconfig"
```

If the build system detects a statement that identifies an "out-of-tree" `defconfig` file, your `KBUILD_DEFCONFIG` variable will take precedence over it.

See the `KBUILD_DEFCONFIG` variable description for more information.

## 9.2.4 Using `devtool` to Patch the Kernel

The steps in this procedure show you how you can patch the kernel using `devtool`.

### Nota

Before attempting this procedure, be sure you have performed the steps to get ready for updating the kernel as described in the *"Getting Ready to Develop Using devtool"* section.

Patching the kernel involves changing or adding configurations to an existing kernel, changing or adding recipes to the kernel that are needed to support specific hardware features, or even altering the source code itself.

This example creates a simple patch by adding some QEMU emulator console output at boot time through `printk` statements in the kernel's `calibrate.c` source code file. Applying the patch and booting the modified image causes the added messages to appear on the emulator's console. The example is a continuation of the setup procedure found in the *"Getting Ready to Develop Using devtool"* Section.

1. *Check Out the Kernel Source Files:* First you must use `devtool` to checkout the kernel source code in its workspace.

**i Nota**

See this step in the "*Getting Ready to Develop Using devtool*" section for more information.

Use the following `devtool` command to check out the code:

```
$ devtool modify linux-yocto
```

2. *Edit the Source Files* Follow these steps to make some simple changes to the source files:

1. *Change the working directory:* In the previous step, the output noted where you can find the source files (e.g. `build/workspace/sources/linux-yocto`). Change to where the kernel source code is before making your edits to the `calibrate.c` file:

```
$ cd build/workspace/sources/linux-yocto
```

2. *Edit the source file:* Edit the `init/calibrate.c` file to have the following changes:

```
void calibrate_delay(void)
{
    unsigned long lpj;
    static bool printed;
    int this_cpu = smp_processor_id();

    printk("*****\n");
    printk("**                               *\n");
    printk("**          HELLO YOCTO KERNEL          *\n");
    printk("**                               *\n");
    printk("*****\n");

    if (per_cpu(cpu_loops_per_jiffy, this_cpu)) {
        .
        .
        .
    }
}
```

3. *Build the Updated Kernel Source:* To build the updated kernel source, use `devtool`:

```
$ devtool build linux-yocto
```

4. *Create the Image With the New Kernel:* Use the `devtool build-image` command to create a new image that has the new kernel:

```
$ cd ~
$ devtool build-image core-image-minimal
```

**i Nota**

If the image you originally created resulted in a Wic file, you can use an alternate method to create the new image with the updated kernel. For an example, see the steps in the [TipsAndTricks/KernelDevelopmentWithEsdk](#) Wiki Page.

5. *Test the New Image:* For this example, you can run the new image using QEMU to verify your changes:

1. *Boot the image:* Boot the modified image in the QEMU emulator using this command:

```
$ runqemu qemux86
```

2. *Verify the changes:* Log into the machine using `root` with no password and then use the following shell command to scroll through the console's boot output.

```
# dmesg | less
```

You should see the results of your `printk` statements as part of the output when you scroll down the console window.

6. *Stage and commit your changes:* Change your working directory to where you modified the `calibrate.c` file and use these Git commands to stage and commit your changes:

```
$ cd build/workspace/sources/linux-yocto
$ git status
$ git add init/calibrate.c
$ git commit -m "calibrate: Add printk example"
```

7. *Export the Patches and Create an Append File:* To export your commits as patches and create a `.bbappend` file, use the following command. This example uses the previously established layer named `meta-mylayer`:

```
$ devtool finish linux-yocto ~/meta-mylayer
```

**i Nota**

See Step 3 of the "[Getting Ready to Develop Using devtool](#)" section for information on setting up this layer.

Once the command finishes, the patches and the `.bbappend` file are located in the `~/meta-mylayer/recipes-kernel/linux` directory.

8. *Build the Image With Your Modified Kernel:* You can now build an image that includes your kernel patches. Execute the following command from your [Build Directory](#) in the terminal set up to run BitBake:

```
$ cd bitbake-builds/build
$ bitbake core-image-minimal
```

## 9.2.5 Using Traditional Kernel Development to Patch the Kernel

The steps in this procedure show you how you can patch the kernel using traditional kernel development (i.e. not using `devtool` as described in the "[Using devtool to Patch the Kernel](#)" section).

### Nota

Before attempting this procedure, be sure you have performed the steps to get ready for updating the kernel as described in the "[Getting Ready for Traditional Kernel Development](#)" section.

Patching the kernel involves changing or adding configurations to an existing kernel, changing or adding recipes to the kernel that are needed to support specific hardware features, or even altering the source code itself.

The example in this section creates a simple patch by adding some QEMU emulator console output at boot time through `printk` statements in the kernel's `calibrate.c` source code file. Applying the patch and booting the modified image causes the added messages to appear on the emulator's console. The example is a continuation of the setup procedure found in the "[Getting Ready for Traditional Kernel Development](#)" Section.

1. *Edit the Source Files* Prior to this step, you should have used Git to create a local copy of the repository for your kernel. Assuming you created the repository as directed in the "[Getting Ready for Traditional Kernel Development](#)" section, use the following commands to edit the `calibrate.c` file:

1. *Change the working directory:* You need to locate the source files in the local copy of the kernel Git repository. Change to where the kernel source code is before making your edits to the `calibrate.c` file:

```
$ cd ~/linux-yocto-4.12/init
```

2. *Edit the source file:* Edit the `calibrate.c` file to have the following changes:

```
void calibrate_delay(void)
{
    unsigned long lpj;
    static bool printed;
    int this_cpu = smp_processor_id();

    printk("*****\n");
    printk("*\n");
    printk("*      HELLO YOCTO KERNEL      *\n");
    printk("*\n");
    printk("*****\n");

    if (per_cpu(cpu_loops_per_jiffy, this_cpu)) {
        .
        .
        .
    }
}
```

2. *Stage and Commit Your Changes:* Use standard Git commands to stage and commit the changes you just made:

```
$ git add calibrate.c
$ git commit -m "calibrate.c - Added some printk statements"
```

If you do not stage and commit your changes, the OpenEmbedded Build System will not pick up the changes.

3. *Update Your local.conf File to Point to Your Source Files:* In addition to your *build/conf/local.conf* file specifying to use "kernel-modules" and the "qemux86" machine, it must also point to the updated kernel source files. Add *SRC\_URI* and *SRCREV* statements similar to the following to your *build/conf/local.conf*:

```
$ cd bitbake-builds/build/conf
```

Add the following to the *build/conf/local.conf*:

```
SRC_URI:pn-linux-yocto = "git:///path-to/linux-yocto-4.12;protocol=file;
→name=machine;branch=standard/base; \
                        git:///path-to/yocto-kernel-cache;protocol=file;
→type=kmeta;name=meta;branch=yocto-4.12;destsuffix=${KMETA}"
SRCREV_meta:qemux86 = "${AUTOREV}"
SRCREV_machine:qemux86 = "${AUTOREV}"
```

#### Nota

Be sure to replace *path-to* with the pathname to your local Git repositories. Also, you must be sure to specify the correct branch and machine types. For this example, the branch is *standard/base* and the machine is *qemux86*.

4. *Build the Image:* With the source modified, your changes staged and committed, and the *build/conf/local.conf* file pointing to the kernel files, you can now use BitBake to build the image:

```
$ cd bitbake-builds/build
$ bitbake core-image-minimal
```

5. *Boot the image:* Boot the modified image in the QEMU emulator using this command. When prompted to login to the QEMU console, use "root" with no password:

```
$ cd bitbake-builds/build
$ runqemu qemux86
```

6. *Look for Your Changes:* As QEMU booted, you might have seen your changes rapidly scroll by. If not, use these commands to see your changes:

```
# dmesg | less
```

You should see the results of your *printk* statements as part of the output when you scroll down the console window.



7. *Generate the Patch File:* Once you are sure that your patch works correctly, you can generate a \*.patch file in the kernel source repository:

```
$ cd ~/linux-yocto-4.12/init
$ git format-patch -1
0001-calibrate.c-Added-some-printk-statements.patch
```

8. *Move the Patch File to Your Layer:* In order for subsequent builds to pick up patches, you need to move the patch file you created in the previous step to your layer `meta-mylayer`. For this example, the layer created earlier is located in your home directory as `meta-mylayer`. When the layer was created using the `yocto-create` script, no additional hierarchy was created to support patches. Before moving the patch file, you need to add additional structure to your layer using the following commands:

```
$ cd ~/meta-mylayer
$ mkdir -p recipes-kernel recipes-kernel/linux/linux-yocto
```

Once you have created this hierarchy in your layer, you can move the patch file using the following command:

```
$ mv ~/linux-yocto-4.12/init/0001-calibrate.c-Added-some-printk-statements.
→patch ~/meta-mylayer/recipes-kernel/linux/linux-yocto
```

9. *Create the Append File:* Finally, you need to create the `linux-yocto_4.12.bbappend` file and insert statements that allow the OpenEmbedded build system to find the patch. The append file needs to be in your layer's `recipes-kernel/linux` directory and it must be named `linux-yocto_4.12.bbappend` and have the following contents:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"
SRC_URI += "file://0001-calibrate.c-Added-some-printk-statements.patch"
```

The `FILESEXTRAPATHS` and `SRC_URI` statements enable the OpenEmbedded build system to find the patch file.

For more information on append files and patches, see the "[Creating the Append File](#)" and "[Applying Patches](#)" sections. You can also see the "[Appending Other Layers Metadata With Your Layer](#)" section in the Yocto Project Development Tasks Manual.

#### Nota

To build `core-image-minimal` again and see the effects of your patch, you can essentially eliminate the temporary source files saved in `bitbake-builds/build/tmp/work/...` and residual effects of the build by entering the following sequence of commands:

```
$ cd bitbake-builds/build
$ bitbake -c cleanall linux-yocto
$ bitbake core-image-minimal -c cleanall
$ bitbake core-image-minimal
$ runqemu qemu86
```

## 9.2.6 Configuring the Kernel

Configuring the Yocto Project kernel consists of making sure the `.config` file has all the right information in it for the image you are building. You can use the `menuconfig` tool and configuration fragments to make sure your `.config` file is just how you need it. You can also save known configurations in a `defconfig` file that the build system can use for kernel configuration.

This section describes how to use `menuconfig`, create and use configuration fragments, and how to interactively modify your `.config` file to create the leanest kernel configuration file possible.

For more information on kernel configuration, see the "*Changing the Configuration*" section.

### Using `menuconfig`

The easiest way to define kernel configurations is to set them through the `menuconfig` tool. This tool provides an interactive method with which to set kernel configurations. For general information on `menuconfig`, see <https://en.wikipedia.org/wiki/Menuconfig>.

To use the `menuconfig` tool in the Yocto Project development environment, you must do the following:

- Because you launch `menuconfig` using BitBake, you must be sure to set up your environment by running the *oe-init-build-env* script found in the *Build Directory*.
- You must be sure of the state of your build's configuration in the *Source Directory*.
- Your build host must have the following two packages installed:

```
libncurses5-dev
libtinfo-dev
```

The following commands initialize the BitBake environment, run the *do\_kernel\_configme* task, and launch `menuconfig`. These commands assume the Source Directory's top-level folder is `work`:

```
$ cd work
$ source layers/openembedded-core/oe-init-build-env
$ bitbake linux-yocto -c kernel_configme -f
$ bitbake linux-yocto -c menuconfig
```

Once `menuconfig` comes up, its standard interface allows you to interactively examine and configure all the kernel configuration parameters. After making your changes, simply exit the tool and save your changes to create an updated version of the `.config` configuration file.

#### Nota

You can use the entire `.config` file as the `defconfig` file. For information on `defconfig` files, see the "*Changing the Configuration*", "*Using an 'In-Tree' defconfig File*", and "*Creating a defconfig File*" sections.

Consider an example that configures the "CONFIG\_SMP" setting for the `linux-yocto-4.12` kernel.

**i Nota**

The OpenEmbedded build system recognizes this kernel as `linux-yocto` through Metadata (e.g. `PREFERRED_VERSION_linux-yocto ?= "4.12%"`).

Once `menuconfig` launches, use the interface to navigate through the selections to find the configuration settings in which you are interested. For this example, you deselect "CONFIG\_SMP" by clearing the "Symmetric Multi-Processing Support" option. Using the interface, you can find the option under "Processor Type and Features". To deselect "CONFIG\_SMP", use the arrow keys to highlight "Symmetric Multi-Processing Support" and enter "N" to clear the asterisk. When you are finished, exit out and save the change.

Saving the selections updates the `.config` configuration file. This is the file that the OpenEmbedded build system uses to configure the kernel during the build. You can find and examine this file in the [Build Directory](#) in `tmp/work/`. The actual `.config` is located in the area where the specific kernel is built. For example, if you were building a Linux Yocto kernel based on the `linux-yocto-4.12` kernel and you were building a QEMU image targeted for x86 architecture, the `.config` file would be:

```
bitbake-builds/build/tmp/work/qemux86-poky-linux/linux-yocto/4.12.
↳ 12+gitAUTOINC+eda4d18...
...967-r0/linux-qemux86-standard-build/.config
```

**i Nota**

The previous example directory is artificially split and many of the characters in the actual filename are omitted in order to make it more readable. Also, depending on the kernel you are using, the exact pathname might differ.

Within the `.config` file, you can see the kernel settings. For example, the following entry shows that symmetric multi-processor support is not set:

```
# CONFIG_SMP is not set
```

A good method to isolate changed configurations is to use a combination of the `menuconfig` tool and simple shell commands. Before changing configurations with `menuconfig`, copy the existing `.config` and rename it to something else, use `menuconfig` to make as many changes as you want and save them, then compare the renamed configuration file against the newly created file. You can use the resulting differences as your base to create configuration fragments to permanently save in your kernel layer.

**i Nota**

Be sure to make a copy of the `.config` file and do not just rename it. The build system needs an existing `.config` file from which to work.

### Creating a `defconfig` File

A `defconfig` file in the context of the Yocto Project is often a `.config` file that is copied from a build or a `defconfig` taken from the kernel tree and moved into recipe space. You can use a `defconfig` file to retain a known set of kernel configurations from which the OpenEmbedded build system can draw to create the final `.config` file.

**i Nota**

Out-of-the-box, the Yocto Project never ships a `defconfig` or `.config` file. The OpenEmbedded build system creates the final `.config` file used to configure the kernel.

To create a `defconfig`, start with a complete, working Linux kernel `.config` file. Copy that file to the appropriate `${PN}` directory in your layer's `recipes-kernel/linux` directory, and rename the copied file to "defconfig" (e.g. `~/meta-mylayer/recipes-kernel/linux/linux-yocto/defconfig`). Then, add the following lines to the `linux-yocto` `.bbappend` file in your layer:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"  
SRC_URI += "file://defconfig"
```

The `SRC_URI` tells the build system how to search for the file, while the `FILESEXTRAPATHS` extends the `FILESPATH` variable (search directories) to include the `${PN}` directory you created to hold the configuration changes.

**i Nota**

The build system applies the configurations from the `defconfig` file before applying any subsequent configuration fragments. The final kernel configuration is a combination of the configurations in the `defconfig` file and any configuration fragments you provide. You need to realize that if you have any configuration fragments, the build system applies these on top of and after applying the existing `defconfig` file configurations.

For more information on configuring the kernel, see the "[Changing the Configuration](#)" section.

### Creating Configuration Fragments

Configuration fragments are simply kernel options that appear in a file placed where the OpenEmbedded build system can find and apply them. The build system applies configuration fragments after applying configurations from a `defconfig` file. Thus, the final kernel configuration is a combination of the configurations in the `defconfig` file and then any configuration fragments you provide. The build system applies fragments on top of and after applying the existing `defconfig` file configurations.

Syntactically, the configuration statement is identical to what would appear in the `.config` file, which is in the [Build Directory](#).

**i Nota**

For more information about where the `.config` file is located, see the example in the "[Using menuconfig](#)" section.

It is simple to create a configuration fragment. One method is to use shell commands. For example, issuing the following from the shell creates a configuration fragment file named `my_changes.cfg` that enables multi-processor support within the kernel and disables the FPGA Configuration Framework:

```
$ echo "CONFIG_SMP=y" >> my_changes.cfg
$ echo "# CONFIG_FPGA is not set" >> my_changes.cfg
```

**i Nota**

All configuration fragment files must use the `.cfg` extension in order for the OpenEmbedded build system to recognize them as a configuration fragment.

Another method is to create a configuration fragment using the differences between two configuration files: one previously created and saved, and one freshly created using the `menuconfig` tool.

To create a configuration fragment using this method, follow these steps:

1. *Complete a Build Through Kernel Configuration:* Complete a build at least through the kernel configuration task as follows:

```
$ bitbake linux-yocto -c kernel_configme -f
```

This step ensures that you create a `.config` file from a known state. Because there are situations where your build state might become unknown, it is best to run this task prior to starting `menuconfig`.

2. *Launch menuconfig:* Run the `menuconfig` command:

```
$ bitbake linux-yocto -c menuconfig
```

3. *Create the Configuration Fragment:* Run the `diffconfig` command to prepare a configuration fragment. The resulting file `fragment.cfg` is placed in the `${WORKDIR}` directory:

```
$ bitbake linux-yocto -c diffconfig
```

The `diffconfig` command creates a file that is a list of Linux kernel `CONFIG_` assignments. See the "[Changing the Configuration](#)" section for additional information on how to use the output as a configuration fragment.

**i Nota**

You can also use this method to create configuration fragments for a BSP. See the "*BSP Descriptions*" section for more information.

Where do you put your configuration fragment files? You can place these files in an area pointed to by *SRC\_URI* as directed by your *build/conf/bblayers.conf* file, which is located in your layer. The OpenEmbedded build system picks up the configuration and adds it to the kernel's configuration. For example, suppose you had a set of configuration options in a file called *myconfig.cfg*. If you put that file inside a directory named *linux-yocto* that resides in the same directory as the kernel's append file within your layer and then add the following statements to the kernel's append file, those configuration options will be picked up and applied when the kernel is built:

```
FILESEXTRAPATHS:prepend := "${THISDIR}/${PN}:"
SRC_URI += "file://myconfig.cfg"
```

As mentioned earlier, you can group related configurations into multiple files and name them all in the *SRC\_URI* statement as well. For example, you could group separate configurations specifically for Ethernet and graphics into their own files and add those by using a *SRC\_URI* statement like the following in your append file:

```
SRC_URI += "file://myconfig.cfg \
           file://eth.cfg \
           file://gfx.cfg"
```

## Validating Configuration

You can use the *do\_kernel\_configcheck* task to provide configuration validation:

```
$ bitbake linux-yocto -c kernel_configcheck -f
```

Running this task produces warnings when a requested configuration does not appear in the final *.config* file or when you override a policy configuration in a hardware configuration fragment.

In order to run this task, you must have an existing *.config* file. See the "*Using menuconfig*" section for information on how to create a configuration file.

Here is sample output from the *do\_kernel\_configcheck* task:

```
Loading cache: 100% |#####|
↪Time: 0:00:00
Loaded 1275 entries from dependency cache.
NOTE: Resolving any missing task queue dependencies

Build Configuration:
.
.
.
```

(continues on next page)

(continua dalla pagina precedente)

```

NOTE: Executing SetScene Tasks
NOTE: Executing RunQueue Tasks
WARNING: linux-yocto-4.12.12+gitAUTOINC+eda4d18ce4_16de014967-r0 do_kernel_
↳configcheck:
    [kernel config]: specified values did not make it into the kernel's final_
↳configuration:

----- CONFIG_X86_TSC -----
Config: CONFIG_X86_TSC
From: /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/bsp/common-pc/common-pc-cpu.cfg
Requested value: CONFIG_X86_TSC=y
Actual value:

----- CONFIG_X86_BIGSMP -----
Config: CONFIG_X86_BIGSMP
From: /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/cfg/smp.cfg
    /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/defconfig
Requested value: # CONFIG_X86_BIGSMP is not set
Actual value:

----- CONFIG_NR_CPUS -----
Config: CONFIG_NR_CPUS
From: /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/cfg/smp.cfg
    /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/bsp/common-pc/common-pc.cfg
    /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/defconfig
Requested value: CONFIG_NR_CPUS=8
Actual value: CONFIG_NR_CPUS=1

----- CONFIG_SCHED_SMT -----
Config: CONFIG_SCHED_SMT
From: /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/cfg/smp.cfg
    /home/scottrif/bitbake-builds/build/tmp/work-shared/qemux86/kernel-source/.
↳kernel-meta/configs/standard/defconfig

```

(continues on next page)

(continua dalla pagina precedente)

```
Requested value: CONFIG_SCHED_SMT=y
Actual value:
```

```
NOTE: Tasks Summary: Attempted 288 tasks of which 285 didn't need to be rerun and
↳all succeeded.
```

```
Summary: There were 3 WARNING messages shown.
```

**i Nota**

The previous output example has artificial line breaks to make it more readable.

The output describes the various problems that you can encounter along with where to find the offending configuration items. You can use the information in the logs to adjust your configuration files and then repeat the `do_kernel_configme` and `do_kernel_configcheck` tasks until they produce no warnings.

For more information on how to use the `menuconfig` tool, see the [Using menuconfig](#) section.

## Fine-Tuning the Kernel Configuration File

You can make sure the `.config` file is as lean or efficient as possible by reading the output of the kernel configuration fragment audit, noting any issues, making changes to correct the issues, and then repeating.

As part of the kernel build process, the `do_kernel_configcheck` task runs. This task validates the kernel configuration by checking the final `.config` file against the input files. During the check, the task produces warning messages for the following issues:

- Requested options that did not make it into the final `.config` file.
- Configuration items that appear twice in the same configuration fragment.
- Configuration items tagged as "required" that were overridden.
- A board overrides a non-board specific option.
- Listed options not valid for the kernel being processed. In other words, the option does not appear anywhere.

**i Nota**

The `do_kernel_configcheck` task can also optionally report if an option is overridden during processing.

For each output warning, a message points to the file that contains a list of the options and a pointer to the configuration fragment that defines them. Collectively, the files are the key to streamlining the configuration.

To streamline the configuration, do the following:



1. *Use a Working Configuration:* Start with a full configuration that you know works. Be sure the configuration builds and boots successfully. Use this configuration file as your baseline.
2. *Run Configure and Check Tasks:* Separately run the `do_kernel_configme` and `do_kernel_configcheck` tasks:

```
$ bitbake linux-yocto -c kernel_configme -f
$ bitbake linux-yocto -c kernel_configcheck -f
```

3. *Process the Results:* Take the resulting list of files from the `do_kernel_configcheck` task warnings and do the following:
  - Drop values that are redefined in the fragment but do not change the final `.config` file.
  - Analyze and potentially drop values from the `.config` file that override required configurations.
  - Analyze and potentially remove non-board specific options.
  - Remove repeated and invalid options.
4. *Re-Run Configure and Check Tasks:* After you have worked through the output of the kernel configuration audit, you can re-run the `do_kernel_configme` and `do_kernel_configcheck` tasks to see the results of your changes. If you have more issues, you can deal with them as described in the previous step.

Iteratively working through steps two through four eventually yields a minimal, streamlined configuration file. Once you have the best `.config`, you can build the Linux Yocto kernel.

## 9.2.7 Expanding Variables

Sometimes it is helpful to determine what a variable expands to during a build. You can examine the value of a variable by running the `bitbake-getvar` command:

```
$ bitbake-getvar -r virtual/kernel VARIABLE
```

The output of the command explains exactly how the variable is expanded and used by the *OpenEmbedded Build System*.

## 9.2.8 Working with a "Dirty" Kernel Version String

If you build a kernel image and the version string has a "+" or a "-dirty" at the end, it means there are uncommitted modifications in the kernel's source directory. Follow these steps to clean up the version string:

1. *Discover the Uncommitted Changes:* Go to the kernel's locally cloned Git repository (source directory) and use the following Git command to list the files that have been changed, added, or removed:

```
$ git status
```

2. *Commit the Changes:* You should commit those changes to the kernel source tree regardless of whether or not you will save, export, or use the changes:

```
$ git add
$ git commit -s -a -m "getting rid of -dirty"
```

3. *Rebuild the Kernel Image:* Once you commit the changes, rebuild the kernel.

Depending on your particular kernel development workflow, the commands you use to rebuild the kernel might differ. For information on building the kernel image when using `devtool`, see the "[Using devtool to Patch the Kernel](#)" section. For information on building the kernel image when using BitBake, see the "[Using Traditional Kernel Development to Patch the Kernel](#)" section.

## 9.2.9 Working With Your Own Sources

If you cannot work with one of the Linux kernel versions supported by existing linux-yocto recipes, you can still make use of the Yocto Project Linux kernel tooling by working with your own sources. When you use your own sources, you will not be able to leverage the existing kernel *Metadata* and stabilization work of the linux-yocto sources. However, you will be able to manage your own Metadata in the same format as the linux-yocto sources. Maintaining format compatibility facilitates converging with linux-yocto on a future, mutually-supported kernel version.

To help you use your own sources, the Yocto Project provides a [linux-yocto custom recipe](#) that uses `kernel.org` sources and the Yocto Project Linux kernel tools for managing kernel Metadata.

Here are some basic steps you can use to work with your own sources:

1. *Create a Copy of the Kernel Recipe:* Copy the `linux-yocto-custom.bb` recipe to your layer and give it a meaningful name. The name should include the version of the Yocto Linux kernel you are using (e.g. `linux-yocto-myproject_4.12.bb`, where "4.12" is the base version of the Linux kernel with which you would be working).
2. *Create a Directory for Your Patches:* In the same directory inside your layer, create a matching directory to store your patches and configuration files (e.g. `linux-yocto-myproject`).
3. *Ensure You Have Configurations:* Make sure you have either a `defconfig` file or configuration fragment files in your layer. When you use the `linux-yocto-custom.bb` recipe, you must specify a configuration. If you do not have a `defconfig` file, you can run the following:

```
$ make defconfig
```

After running the command, copy the resulting `.config` file to the `files` directory in your layer as "defconfig" and then add it to the `SRC_URI` variable in the recipe.

Running the `make defconfig` command results in the default configuration for your architecture as defined by your kernel. However, there is no guarantee that this configuration is valid for your use case, or that your board will even boot. This is particularly true for non-x86 architectures.

To use non-x86 `defconfig` files, you need to be more specific and find one that matches your board (i.e. for arm, you look in `arch/arm/configs` and use the one that is the best starting point for your board).

4. *Edit the Recipe:* Edit the following variables in your recipe as appropriate for your project:
  - `SRC_URI`: The `SRC_URI` should specify a Git repository that uses one of the supported Git fetcher protocols (i.e. `file`, `git`, `http`, and so forth). The `SRC_URI` variable should also specify either a `defconfig` file or some configuration fragment files. The skeleton recipe provides an example `SRC_URI` as a syntax reference.
  - `LINUX_VERSION`: The Linux kernel version you are using (e.g. "4.12").

- **LINUX\_VERSION\_EXTENSION**: The Linux kernel `CONFIG_LOCALVERSION` that is compiled into the resulting kernel and visible through the `uname` command.
- **SRCREV**: The commit ID from which you want to build.
- **PR**: Treat this variable the same as you would in any other recipe. Increment the variable to indicate to the OpenEmbedded build system that the recipe has changed.
- **PV**: The default **PV** assignment is typically adequate. It combines the value of **LINUX\_VERSION** and the value `+git` which adds source control information to **PKGVERSION** later during the packaging phase.
- **COMPATIBLE\_MACHINE**: A list of the machines supported by your new recipe. This variable in the example recipe is set by default to a regular expression that matches only the empty string, `"(^$)"`. This default setting triggers an explicit build failure. You must change it to match a list of the machines that your new recipe supports. For example, to support the `qemux86` and `qemux86-64` machines, use the following form:

```
COMPATIBLE_MACHINE = "qemux86|qemux86-64"
```

5. *Customize Your Recipe as Needed*: Provide further customizations to your recipe as needed just as you would customize an existing linux-yocto recipe. See the "*Modifying an Existing Recipe*" section for information.

## 9.2.10 Working with Out-of-Tree Modules

This section describes steps to build out-of-tree modules on your target and describes how to incorporate out-of-tree modules in the build.

### Building Out-of-Tree Modules on the Target

While the traditional Yocto Project development model would be to include kernel modules as part of the normal build process, you might find it useful to build modules on the target. This could be the case if your target system is capable and powerful enough to handle the necessary compilation. Before deciding to build on your target, however, you should consider the benefits of using a proper cross-development environment from your build host.

If you want to be able to build out-of-tree modules on the target, there are some steps you need to take on the target that is running your SDK image. Briefly, the `kernel-dev` package is installed by default on all `*.sdk` images and the `kernel-devsrc` package is installed on many of the `*.sdk` images. However, you need to create some scripts prior to attempting to build the out-of-tree modules on the target that is running that image.

Prior to attempting to build the out-of-tree modules, you need to be on the target as root and you need to change to the `/usr/src/kernel` directory. Next, make the scripts:

```
# cd /usr/src/kernel
# make scripts
```

Because all SDK image recipes include `dev-pkgs`, the `kernel-dev` packages will be installed as part of the SDK image and the `kernel-devsrc` packages will be installed as part of applicable SDK images. The SDK uses the scripts when building out-of-tree modules. Once you have switched to that directory and created the scripts, you should be able to build your out-of-tree modules on the target.

## Incorporating Out-of-Tree Modules

While it is always preferable to work with sources integrated into the Linux kernel sources, if you need an external kernel module, the `hello-mod` recipe is available as a template from which you can create your own out-of-tree Linux kernel module recipe.

To get started, copy this recipe to your layer and give it a meaningful name (e.g. `mymodule_1.0.bb`). In the same directory, create a new directory named `files` where you can store any source files, patches, or other files necessary for building the module that do not come with the sources. Finally, update the recipe as needed for the module. Typically, you will need to set the following variables:

- *DESCRIPTION*
- *LICENSE\**
- *SRC\_URI*
- *PV*

Depending on the build system used by the module sources, you might need to make some adjustments. For example, a typical module `Makefile` looks much like the one provided with the `hello-mod` template:

```
obj-m := hello.o

SRC := $(shell pwd)

all:
    $(MAKE) -C $(KERNEL_SRC) M=$(SRC)

modules_install:
    $(MAKE) -C $(KERNEL_SRC) M=$(SRC) modules_install

...
```

The important point to note here is the *KERNEL\_SRC* variable. The *module* class sets this variable and the *KERNEL\_PATH* variable to `${STAGING_KERNEL_DIR}` with the necessary Linux kernel build information to build modules. If your module `Makefile` uses a different variable, you might want to override the *do\_compile* step, or create a patch to the `Makefile` to work with the more typical *KERNEL\_SRC* or *KERNEL\_PATH* variables.

After you have prepared your recipe, you will likely want to include the module in your images. To do this, see the documentation for the following variables in the Yocto Project Reference Manual and set one of them appropriately for your machine configuration file:

- *MACHINE\_ESSENTIAL\_EXTRA\_RDEPENDS*
- *MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS*
- *MACHINE\_EXTRA\_RDEPENDS*
- *MACHINE\_EXTRA\_RRECOMMENDS*

Modules are often not required for boot and can be excluded from certain build configurations. The following allows for the most flexibility:

```
MACHINE_EXTRA_RRECOMMENDS += "kernel-module-mymodule"
```

The value is derived by appending the module filename without the `.ko` extension to the string "kernel-module-".

Because the variable is *RRECOMMENDS* and not a *RDEPENDS* variable, the build will not fail if this module is not available to include in the image.

### 9.2.11 Inspecting Changes and Commits

A common question when working with a kernel is: "What changes have been applied to this tree?" Rather than using "grep" across directories to see what has changed, you can use Git to inspect or search the kernel tree. Using Git is an efficient way to see what has changed in the tree.

#### What Changed in a Kernel?

Here are a few examples that show how to use Git commands to examine changes. These examples are by no means the only way to see changes.

#### Nota

In the following examples, unless you provide a commit range, `kernel.org` history is blended with Yocto Project kernel changes. You can form ranges by using branch names from the kernel tree as the upper and lower commit markers with the Git commands. You can see the branch names through the web interface to the Yocto Project source repositories at <https://git.yoctoproject.org/>.

To see a full range of the changes, use the `git whatchanged` command and specify a commit range for the branch (`commit..commit`).

Here is an example that looks at what has changed in the `emenlow` branch of the `linux-yocto-3.19` kernel. The lower commit range is the commit associated with the `standard/base` branch, while the upper commit range is the commit associated with the `standard/emenlow` branch:

```
$ git whatchanged origin/standard/base..origin/standard/emenlow
```

To see short, one line summaries of changes use the `git log` command:

```
$ git log --oneline origin/standard/base..origin/standard/emenlow
```

Use this command to see code differences for the changes:

```
$ git diff origin/standard/base..origin/standard/emenlow
```

Use this command to see the commit log messages and the text differences:

```
$ git show origin/standard/base..origin/standard/emenlow
```

Use this command to create individual patches for each change. Here is an example that creates patch files for each commit and places them in your `Documents` directory:

```
$ git format-patch -o $HOME/Documents origin/standard/base..origin/standard/emenlow
```

### Showing a Particular Feature or Branch Change

Tags in the Yocto Project kernel tree divide changes for significant features or branches. The `git show tag` command shows changes based on a tag. Here is an example that shows `systemtap` changes:

```
$ git show systemtap
```

You can use the `git branch --contains tag` command to show the branches that contain a particular feature. This command shows the branches that contain the `systemtap` feature:

```
$ git branch --contains systemtap
```

## 9.2.12 Adding Recipe-Space Kernel Features

You can add kernel features in the *recipe-space* by using the `KERNEL_FEATURES` variable and by specifying the feature's `.scd` file path in the `SRC_URI` statement. When you add features using this method, the OpenEmbedded build system checks to be sure the features are present. If the features are not present, the build stops. Kernel features are the last elements processed for configuring and patching the kernel. Therefore, adding features in this manner is a way to enforce specific features are present and enabled without needing to do a full audit of any other layer's additions to the `SRC_URI` statement.

You add a kernel feature by providing the feature as part of the `KERNEL_FEATURES` variable and by providing the path to the feature's `.scd` file, which is relative to the root of the kernel Metadata. The OpenEmbedded build system searches all forms of kernel Metadata on the `SRC_URI` statement regardless of whether the Metadata is in the "kernel-cache", system kernel Metadata, or a recipe-space Metadata (i.e. part of the kernel recipe). See the "[Kernel Metadata Location](#)" section for additional information.

When you specify the feature's `.scd` file on the `SRC_URI` statement, the OpenEmbedded build system adds the directory of that `.scd` file along with all its subdirectories to the kernel feature search path. Because subdirectories are searched, you can reference a single `.scd` file in the `SRC_URI` statement to reference multiple kernel features.

Consider the following example that adds the "test.scd" feature to the build.

1. *Create the Feature File:* Create a `.scd` file and locate it just as you would any other patch file, `.cfg` file, or fetcher item you specify in the `SRC_URI` statement.

#### Nota

- You must add the directory of the `.scd` file to the fetcher's search path in the same manner as you would add a `.patch` file.
- You can create additional `.scd` files beneath the directory that contains the file you are adding. All subdirectories are searched during the build as potential feature directories.

Continuing with the example, suppose the "test.scd" feature you are adding has a `test.scd` file in the following directory:

```
my_recipe
|
+-linux-yocto
|
+-test.cfg
+-test.scc
```

In this example, the `linux-yocto` directory has both the feature `test.scc` file and a similarly named configuration fragment file `test.cfg`.

2. *Add the Feature File to SRC\_URI:* Add the `.scc` file to the recipe's `SRC_URI` statement:

```
SRC_URI += "file://test.scc"
```

The leading space before the path is important as the path is appended to the existing path.

3. *Specify the Feature as a Kernel Feature:* Use the `KERNEL_FEATURES` statement to specify the feature as a kernel feature:

```
KERNEL_FEATURES += "test.scc"
```

The OpenEmbedded build system processes the kernel feature when it builds the kernel.

#### Nota

If other features are contained below "test.scc", then their directories are relative to the directory containing the `test.scc` file.

## 9.3 Working with Advanced Metadata (yocto-kernel-cache)

### 9.3.1 Overview

In addition to supporting configuration fragments and patches, the Yocto Project kernel tools also support rich *Metadata* that you can use to define complex policies and Board Support Package (BSP) support. The purpose of the Metadata and the tools that manage it is to help you manage the complexity of the configuration and sources used to support multiple BSPs and Linux kernel types.

Kernel Metadata exists in many places. One area in the *I Repository del Codice Sorgente di Yocto Project* is the `yocto-kernel-cache` Git repository. You can find this repository grouped under the "Yocto Linux Kernel" heading in the [Yocto Project Source Repositories](#).

Kernel development tools ("kern-tools") are also available in the Yocto Project Source Repositories under the "Yocto Linux Kernel" heading in the `yocto-kernel-tools` Git repository. The recipe that builds these tools is `recipes-kernel/kern-tools/kern-tools-native_git.bb` in *OpenEmbedded-Core (OE-Core)*.

### 9.3.2 Using Kernel Metadata in a Recipe

As mentioned in the introduction, the Yocto Project contains kernel Metadata, which is located in the `yocto-to-kernel-cache` Git repository. This Metadata defines Board Support Packages (BSPs) that correspond to definitions in linux-yocto recipes for corresponding BSPs. A BSP consists of an aggregation of kernel policy and enabled hardware-specific features. The BSP can be influenced from within the linux-yocto recipe.

#### Nota

A Linux kernel recipe that contains kernel Metadata (e.g. inherits from the `linux-yocto.inc` file) is said to be a "linux-yocto style" recipe.

Every linux-yocto style recipe must define the `KMACHINE` variable. This variable is typically set to the same value as the `MACHINE` variable, which is used by *BitBake*. However, in some cases, the variable might instead refer to the underlying platform of the `MACHINE`.

Multiple BSPs can reuse the same `KMACHINE` name if they are built using the same BSP description. Multiple Corei7-based BSPs could share the same "intel-corei7-64" value for `KMACHINE`. It is important to realize that `KMACHINE` is just for kernel mapping, while `MACHINE` is the machine type within a BSP Layer. Even with this distinction, however, these two variables can hold the same value. See the "*BSP Descriptions*" section for more information.

Every linux-yocto style recipe must also indicate the Linux kernel source repository branch used to build the Linux kernel. The `KBRANCH` variable must be set to indicate the branch.

#### Nota

You can use the `KBRANCH` value to define an alternate branch typically with a machine override as shown here from the `meta-yocto-bsp` layer:

```
KBRANCH:beaglebone-yocto = "standard/beaglebone"
```

The linux-yocto style recipes can optionally define the following variables:

- `KERNEL_FEATURES`
- `LINUX_KERNEL_TYPE`

`LINUX_KERNEL_TYPE` defines the kernel type to be used in assembling the configuration. If you do not specify a `LINUX_KERNEL_TYPE`, it defaults to "standard". Together with `KMACHINE`, `LINUX_KERNEL_TYPE` defines the search arguments used by the kernel tools to find the appropriate description within the kernel Metadata with which to build out the sources and configuration. The linux-yocto recipes define "standard", "tiny", and "preempt-rt" kernel types. See the "*Kernel Types*" section for more information on kernel types.

During the build, the kern-tools search for the BSP description file that most closely matches the `KMACHINE` and `LINUX_KERNEL_TYPE` variables passed in from the recipe. The tools use the first BSP description they find that matches both variables. If the tools cannot find a match, they issue a warning.



The tools first search for the *KMACHINE* and then for the *LINUX\_KERNEL\_TYPE*. If the tools cannot find a partial match, they will use the sources from the *KBRANCH* and any configuration specified in the *SRC\_URI*.

You can use the *KERNEL\_FEATURES* variable to include features (configuration fragments, patches, or both) that are not already included by the *KMACHINE* and *LINUX\_KERNEL\_TYPE* variable combination. For example, to include a feature specified as "features/netfilter/netfilter.scc", specify:

```
KERNEL_FEATURES += "features/netfilter/netfilter.scc"
```

To include a feature called "cfg/sound.scc" just for the *qemux86* machine, specify:

```
KERNEL_FEATURES:append:qemux86 = " cfg/sound.scc"
```

The value of the entries in *KERNEL\_FEATURES* are dependent on their location within the kernel Metadata itself. The examples here are taken from the *yocto-kernel-cache* repository. Each branch of this repository contains "features" and "cfg" subdirectories at the top-level. For more information, see the "*Kernel Metadata Syntax*" section.

### 9.3.3 Kernel Metadata Syntax

The kernel Metadata consists of three primary types of files: *scc*<sup>1</sup> description files, configuration fragments, and patches. The *scc* files define variables and include or otherwise reference any of the three file types. The description files are used to aggregate all types of kernel Metadata into what ultimately describes the sources and the configuration required to build a Linux kernel tailored to a specific machine.

The *scc* description files are used to define two fundamental types of kernel Metadata:

- Caratteristiche
- Board Support Packages (BSPs)

Features aggregate sources in the form of patches and configuration fragments into a modular reusable unit. You can use features to implement conceptually separate kernel Metadata descriptions such as pure configuration fragments, simple patches, complex features, and kernel types. *Kernel Types* define general kernel features and policy to be reused in the BSPs.

BSPs define hardware-specific features and aggregate them with kernel types to form the final description of what will be assembled and built.

While the kernel Metadata syntax does not enforce any logical separation of configuration fragments, patches, features or kernel types, best practices dictate a logical separation of these types of Metadata. The following Metadata file hierarchy is recommended:

```
base/
  bsp/
  cfg/
  features/
  ktypes/
  patches/
```

<sup>1</sup> *scc* stands for Series Configuration Control, but the naming has less significance in the current implementation of the tooling than it had in the past. Consider *scc* files to be description files.

The `bsp` directory contains the *BSP Descriptions*. The remaining directories all contain "features". Separating `bsp` from the rest of the structure aids conceptualizing intended usage.

Use these guidelines to help place your `scc` description files within the structure:

- If your file contains only configuration fragments, place the file in the `cfg` directory.
- If your file contains only source-code fixes, place the file in the `patches` directory.
- If your file encapsulates a major feature, often combining sources and configurations, place the file in `features` directory.
- If your file aggregates non-hardware configuration and patches in order to define a base kernel policy or major kernel type to be reused across multiple BSPs, place the file in `ktypes` directory.

These distinctions can easily become blurred --- especially as out-of-tree features slowly merge upstream over time. Also, remember that how the description files are placed is a purely logical organization and has no impact on the functionality of the kernel Metadata. There is no impact because all of `cfg`, `features`, `patches`, and `ktypes`, contain "features" as far as the kernel tools are concerned.

Paths used in kernel Metadata files are relative to base, which is either *FILESEXTRAPATHS* if you are creating Metadata in *recipe-space*, or the top level of *yocto-kernel-cache* if you are creating *Metadata Outside the Recipe-Space*.

## Configuration

The simplest unit of kernel Metadata is the configuration-only feature. This feature consists of one or more Linux kernel configuration parameters in a configuration fragment file (`.cfg`) and a `.scc` file that describes the fragment.

As an example, consider the Symmetric Multi-Processing (SMP) fragment used with the `linux-yocto-4.12` kernel as defined outside of the recipe space (i.e. *yocto-kernel-cache*). This Metadata consists of two files: `smp.scc` and `smp.cfg`. You can find these files in the `cfg` directory of the `yocto-4.12` branch in the *yocto-kernel-cache* Git repository:

```
cfg/smp.scc:
define KFEATURE_DESCRIPTION "Enable SMP for 32 bit builds"
define KFEATURE_COMPATIBILITY all

kconf hardware smp.cfg

cfg/smp.cfg:
CONFIG_SMP=y
CONFIG_SCHED_SMT=y
# Increase default NR_CPUS from 8 to 64 so that platform with
# more than 8 processors can be all activated at boot time
CONFIG_NR_CPUS=64
# The following is needed when setting NR_CPUS to something
# greater than 8 on x86 architectures, it should be automatically
# disregarded by Kconfig when using a different arch
CONFIG_X86_BIGSMP=y
```

You can find general information on configuration fragment files in the "*Creating Configuration Fragments*" section.

Within the `smp.scc` file, the *KFEATURE\_DESCRIPTION* statement provides a short description of the fragment. Higher level kernel tools use this description.

Also within the `smp.scc` file, the `kconf` command includes the actual configuration fragment in an `.scc` file, and the "hardware" keyword identifies the fragment as being hardware enabling, as opposed to general policy, which would use the "non-hardware" keyword. The distinction is made for the benefit of the configuration validation tools, which warn you if a hardware fragment overrides a policy set by a non-hardware fragment.

### Nota

The description file can include multiple `kconf` statements, one per fragment.

As described in the "*Validating Configuration*" section, you can use the following BitBake command to audit your configuration:

```
$ bitbake linux-yocto -c kernel_configcheck -f
```

## Patches

Patch descriptions are very similar to configuration fragment descriptions, which are described in the previous section. However, instead of a `.cfg` file, these descriptions work with source patches (i.e. `.patch` files).

A typical patch includes a description file and the patch itself. As an example, consider the build patches used with the `linux-yocto-4.12` kernel as defined outside of the recipe space (i.e. `yocto-kernel-cache`). This Metadata consists of several files: `build.scc` and a set of `*.patch` files. You can find these files in the `patches/build` directory of the `yocto-4.12` branch in the `yocto-kernel-cache` Git repository.

The following listings show the `build.scc` file and part of the `modpost-mask-trivial-warnings.patch` file:

```
patches/build/build.scc:
    patch arm-serialize-build-targets.patch
    patch powerpc-serialize-image-targets.patch
    patch kbuild-exclude-meta-directory-from-distclean-processi.patch

    # applied by kgit
    # patch kbuild-add-meta-files-to-the-ignore-li.patch

    patch modpost-mask-trivial-warnings.patch
    patch menuconfig-check-lxdiaglog.sh-Allow-specification-of.patch

patches/build/modpost-mask-trivial-warnings.patch:
    From bd48931bc142bdd104668f3a062a1f22600aae61 Mon Sep 17 00:00:00 2001
    From: Paul Gortmaker <paul.gortmaker@windriver.com>
    Date: Sun, 25 Jan 2009 17:58:09 -0500
    Subject: [PATCH] modpost: mask trivial warnings

    Newer HOSTCC will complain about various stdio fcns because
```

(continues on next page)

(continua dalla pagina precedente)

```

        .
        .
        .

char *dump_write = NULL, *files_source = NULL;
int opt;

--

2.10.1

generated by cgit v0.10.2 at 2017-09-28 15:23:23 (GMT)

```

The description file can include multiple patch statements where each statement handles a single patch. In the example `build.scc` file, there are five patch statements for the five patches in the directory.

You can create a typical `.patch` file using `diff -Nurp` or `git format-patch` commands. For information on how to create patches, see the "[Using devtool to Patch the Kernel](#)" and "[Using Traditional Kernel Development to Patch the Kernel](#)" sections.

## Caratteristiche

Features are complex kernel Metadata types that consist of configuration fragments, patches, and possibly other feature description files. As an example, consider the following generic listing:

```

features/myfeature.scc
    define KFEATURE_DESCRIPTION "Enable myfeature"

    patch 0001-myfeature-core.patch
    patch 0002-myfeature-interface.patch

    include cfg/myfeature_dependency.scc
    kconf non-hardware myfeature.cfg

```

This example shows how the `patch` and `kconf` commands are used as well as how an additional feature description file is included with the `include` command.

Typically, features are less granular than configuration fragments and are more likely than configuration fragments and patches to be the types of things you want to specify in the `KERNEL_FEATURES` variable of the Linux kernel recipe. See the "[Using Kernel Metadata in a Recipe](#)" section earlier in the manual.

## Kernel Types

A kernel type defines a high-level kernel policy by aggregating non-hardware configuration fragments with patches you want to use when building a Linux kernel of a specific type (e.g. a real-time kernel). Syntactically, kernel types are no different than features as described in the "[Caratteristiche](#)" section. The `LINUX_KERNEL_TYPE` variable in the kernel recipe selects the kernel type. For example, in the `linux-yocto_4.12.bb` kernel recipe found in `meta/recipes-kernel/linux`, a `require` directive includes the `meta/recipes-kernel/linux/linux-yocto.inc` file, which has the following statement that defines the default kernel type:

```
LINUX_KERNEL_TYPE ??= "standard"
```

Another example would be the real-time kernel (i.e. `linux-yocto-rt_4.12.bb`). This kernel recipe directly sets the kernel type as follows:

```
LINUX_KERNEL_TYPE = "preempt-rt"
```

### Nota

You can find kernel recipes in the `meta/recipes-kernel/linux` directory of the *I Repository del Codice Sorgente di Yocto Project*. See the *"Using Kernel Metadata in a Recipe"* section for more information.

Three kernel types ("standard", "tiny", and "preempt-rt") are supported for Linux Yocto kernels:

- "standard": Includes the generic Linux kernel policy of the Yocto Project `linux-yocto` kernel recipes. This policy includes, among other things, which file systems, networking options, core kernel features, and debugging and tracing options are supported.
- "preempt-rt": Applies the `PREEMPT_RT` patches and the configuration options required to build a real-time Linux kernel. This kernel type inherits from the "standard" kernel type.
- "tiny": Defines a bare minimum configuration meant to serve as a base for very small Linux kernels. The "tiny" kernel type is independent from the "standard" configuration. Although the "tiny" kernel type does not currently include any source changes, it might in the future.

For any given kernel type, the Metadata is defined by the `.scc` (e.g. `standard.scc`). Here is a partial listing for the `standard.scc` file, which is found in the `ktypes/standard` directory of the `yocto-kernel-cache` Git repository:

```
# Include this kernel type fragment to get the standard features and
# configuration values.

# Note: if only the features are desired, but not the configuration
#       then this should be included as:
#       include ktypes/standard/standard.scc nocfg
#       if no chained configuration is desired, include it as:
#       include ktypes/standard/standard.scc nocfg inherit

include ktypes/base/base.scc
branch standard

kconf non-hardware standard.cfg

include features/kgdb/kgdb.scc
```

(continues on next page)

(continua dalla pagina precedente)

```
.  
. .  
. .  
. .  
  
include cfg/net/ip6_nf.scc  
include cfg/net/bridge.scc  
  
include cfg/systemd.scc  
  
include features/rfkill/rfkill.scc
```

As with any `.scc` file, a kernel type definition can aggregate other `.scc` files with `include` commands. These definitions can also directly pull in configuration fragments and patches with the `kconf` and `patch` commands, respectively.

**i Nota**

It is not strictly necessary to create a kernel type `.scc` file. The Board Support Package (BSP) file can implicitly define the kernel type using a `define KTYPE myktype` line. See the "[BSP Descriptions](#)" section for more information.

## BSP Descriptions

BSP descriptions (i.e. `*.scc` files) combine kernel types with hardware-specific features. The hardware-specific Metadata is typically defined independently in the BSP layer, and then aggregated with each supported kernel type.

**i Nota**

For BSPs supported by the Yocto Project, the BSP description files are located in the `bsp` directory of the `yocto-kernel-cache` repository organized under the "Yocto Linux Kernel" heading in the [Yocto Project Source Repositories](#).

This section overviews the BSP description structure, the aggregation concepts, and presents a detailed example using a BSP supported by the Yocto Project (i.e. BeagleBone Board). For complete information on BSP layer file hierarchy, see the [Manuale del Board Support Package \(BSP\) di Yocto Project](#).

## Description Overview

For simplicity, consider the following root BSP layer description files for the BeagleBone board. These files employ both a structure and naming convention for consistency. The naming convention for the file is as follows:

```
bsp_root_name-kernel_type.scc
```

Here are some example root layer BSP filenames for the BeagleBone Board BSP, which is supported by the Yocto Project:

```
beaglebone-standard.scc
beaglebone-preempt-rt.scc
```

Each file uses the root name (i.e "beaglebone") BSP name followed by the kernel type.

Examine the `beaglebone-standard.scc` file:

```
define KMACHINE beaglebone
define KTYPE standard
define KARCH arm

include ktypes/standard/standard.scc
branch beaglebone

include beaglebone.scc

# default policy for standard kernels
include features/latencytop/latencytop.scc
include features/profiling/profiling.scc
```

Every top-level BSP description file should define the *KMACHINE*, *KTYPE*, and *KARCH* variables. These variables allow the OpenEmbedded build system to identify the description as meeting the criteria set by the recipe being built. This example supports the "beaglebone" machine for the "standard" kernel and the "arm" architecture.

Be aware that there is no hard link between the *KTYPE* variable and a kernel type description file. Thus, if you do not have the kernel type defined in your kernel Metadata as it is here, you only need to ensure that the *LINUX\_KERNEL\_TYPE* variable in the kernel recipe and the *KTYPE* variable in the BSP description file match.

To separate your kernel policy from your hardware configuration, you include a kernel type (*ktype*), such as "standard". In the previous example, this is done using the following:

```
include ktypes/standard/standard.scc
```

This file aggregates all the configuration fragments, patches, and features that make up your standard kernel policy. See the "*Kernel Types*" section for more information.

To aggregate common configurations and features specific to the kernel for *mybsp*, use the following:

```
include mybsp.scc
```

You can see that in the BeagleBone example with the following:

```
include beaglebone.scc
```

For information on how to break a complete `.config` file into the various configuration fragments, see the "*Creating Configuration Fragments*" section.

Finally, if you have any configurations specific to the hardware that are not in a `*.scc` file, you can include them as follows:

```
kconf hardware mybsp-extra.cfg
```

The BeagleBone example does not include these types of configurations. However, the Malta 32-bit board does ("mti-malta32"). Here is the `mti-malta32-le-standard.scc` file:

```
define KMACHINE mti-malta32-le
define KMACHINE qemuipisel
define KTYPE standard
define KARCH mips

include ktypes/standard/standard.scc
branch mti-malta32

include mti-malta32.scc
kconf hardware mti-malta32-le.cfg
```

## Example

Many real-world examples are more complex. Like any other `.scc` file, BSP descriptions can aggregate features. Consider the Minnow BSP definition given the `linux-yocto-4.4` branch of the `yocto-kernel-cache` (i.e. `yocto-kernel-cache/bsp/minnow/minnow.scc`):

```
include cfg/x86.scc
include features/eg20t/eg20t.scc
include cfg/dmaengine.scc
include features/power/intel.scc
include cfg/efi.scc
include features/usb/ehci-hcd.scc
include features/usb/ohci-hcd.scc
include features/usb/usb-gadgets.scc
include features/usb/touchscreen-composite.scc
include cfg/timer/hpet.scc
include features/leds/leds.scc
include features/spi/spidev.scc
include features/i2c/i2cdev.scc
include features/mei/mei-txe.scc

# Earlyprintk and port debug requires 8250
kconf hardware cfg/8250.cfg

kconf hardware minnow.cfg
kconf hardware minnow-dev.cfg
```



**i Nota**

Although the Minnow Board BSP is unused, the Metadata remains and is being used here just as an example.

The `minnow.scc` description file includes a hardware configuration fragment (`minnow.cfg`) specific to the Minnow BSP as well as several more general configuration fragments and features enabling hardware found on the machine. This `minnow.scc` description file is then included in each of the three "minnow" description files for the supported kernel types (i.e. "standard", "preempt-rt", and "tiny"). Consider the "minnow" description for the "standard" kernel type (i.e. `minnow-standard.scc`):

```
define KMACHINE minnow
define KTYPE standard
define KARCH i386

include ktypes/standard

include minnow.scc

# Extra minnow configs above the minimal defined in minnow.scc
include cfg/efi-ext.scc
include features/media/media-all.scc
include features/sound/snd_hda_intel.scc

# The following should really be in standard.scc
# USB live-image support
include cfg/usb-mass-storage.scc
include cfg/boot-live.scc

# Basic profiling
include features/latencytop/latencytop.scc
include features/profiling/profiling.scc

# Requested drivers that don't have an existing scc
kconf hardware minnow-drivers-extra.cfg
```

The `include` command midway through the file includes the `minnow.scc` description that defines all enabled hardware for the BSP that is common to all kernel types. Using this command significantly reduces duplication.

Now consider the "minnow" description for the "tiny" kernel type (i.e. `minnow-tiny.scc`):

```
define KMACHINE minnow
define KTYPE tiny
define KARCH i386

include ktypes/tiny
```

(continues on next page)

```
include minnow.scc
```

As you might expect, the "tiny" description includes quite a bit less. In fact, it includes only the minimal policy defined by the "tiny" kernel type and the hardware-specific configuration required for booting the machine along with the most basic functionality of the system as defined in the base "minnow" description file.

Notice again the three critical variables: *KMACHINE*, *KTYPE*, and *KARCH*. Of these variables, only *KTYPE* has changed to specify the "tiny" kernel type.

### 9.3.4 Kernel Metadata Location

Kernel Metadata always exists outside of the kernel tree either defined in a kernel recipe (recipe-space) or outside of the recipe. Where you choose to define the Metadata depends on what you want to do and how you intend to work. Regardless of where you define the kernel Metadata, the syntax used applies equally.

If you are unfamiliar with the Linux kernel and only wish to apply a configuration and possibly a couple of patches provided to you by others, the recipe-space method is recommended. This method is also a good approach if you are working with Linux kernel sources you do not control or if you just do not want to maintain a Linux kernel Git repository on your own. For partial information on how you can define kernel Metadata in the recipe-space, see the *"Modifying an Existing Recipe"* section.

Conversely, if you are actively developing a kernel and are already maintaining a Linux kernel Git repository of your own, you might find it more convenient to work with kernel Metadata kept outside the recipe-space. Working with Metadata in this area can make iterative development of the Linux kernel more efficient outside of the BitBake environment.

#### Recipe-Space Metadata

When stored in recipe-space, the kernel Metadata files reside in a directory hierarchy below *FILESEXTRAPATHS*. For a linux-yocto recipe or for a Linux kernel recipe derived by copying `meta-skeleton/recipes-kernel/linux/linux-yocto-custom.bb` into your layer and modifying it, *FILESEXTRAPATHS* is typically set to `${THISDIR}/${PN}`. See the *"Modifying an Existing Recipe"* section for more information.

Here is an example that shows a trivial tree of kernel Metadata stored in recipe-space within a BSP layer:

```
meta-my_bsp_layer/
`-- recipes-kernel
    -- linux
        -- linux-yocto
            -- bsp-standard.scc
            -- bsp.cfg
            -- standard.cfg
```

When the Metadata is stored in recipe-space, you must take steps to ensure BitBake has the necessary information to decide what files to fetch and when they need to be fetched again. It is only necessary to specify the `.scc` files on the *SRC\_URI*. BitBake parses them and fetches any files referenced in the `.scc` files by the `include`, `patch`, or

`kconf` commands. Because of this, it is necessary to bump the recipe *PR* value when changing the content of files not explicitly listed in the *SRC\_URI*.

If the BSP description is in recipe space, you cannot simply list the `*.scc` in the *SRC\_URI* statement. You need to use the following form from your kernel append file:

```
SRC_URI:append:myplatform = " \
    file://myplatform;type=kmeta;destsuffix=myplatform \
"
```

The `type=kmeta` attribute is significant: it adds the directory to the kernel Metadata that the tools search to *discover* the BSP description matching *KMACHINE* and `LINUX_KERNEL_TYPE`. A `.scc` file listed directly on *SRC\_URI* (for example `file://myplatform.scc`) is instead treated as a configuration fragment and is processed in both the configuration and the patch phases. Any `patch` directives that such a fragment references, or that are reached through files it includes (such as an `arch/` or `bsp/` description), are then applied to the kernel source and will fail if those patches are already present in the branch. See the "*Patch Application for BSP Descriptions*" section for the reasoning behind this.

## Metadata Outside the Recipe-Space

When stored outside of the recipe-space, the kernel Metadata files reside in a separate repository. The OpenEmbedded build system adds the Metadata to the build as a "type=kmeta" repository through the *SRC\_URI* variable. As an example, consider the following *SRC\_URI* statement from the `linux-yocto_5.15.bb` kernel recipe:

```
SRC_URI = "https://git.yoctoproject.org/linux-yocto.git;name=machine;branch=$
↪{KBRANCH};protocol=https \
    https://git.yoctoproject.org/yocto-kernel-cache;type=kmeta;name=meta;
↪branch=yocto-5.15;destsuffix=${KMETA};protocol=https"
```

`${KMETA}`, in this context, is simply used to name the directory into which the Git fetcher places the Metadata. This behavior is no different than any multi-repository *SRC\_URI* statement used in a recipe (e.g. see the previous section).

You can keep kernel Metadata in a "kernel-cache", which is a directory containing configuration fragments. As with any Metadata kept outside the recipe-space, you simply need to use the *SRC\_URI* statement with the "type=kmeta" attribute. Doing so makes the kernel Metadata available during the configuration phase.

If you modify the Metadata, you must not forget to update the *SRCREV* statements in the kernel's recipe. In particular, you need to update the `SRCREV_meta` variable to match the commit in the `KMETA` branch you wish to use. Changing the data in these branches and not updating the *SRCREV* statements to match will cause the build to fetch an older commit.

## Patch Application for BSP Descriptions

During the build, the kernel tools search the kernel Metadata for the BSP description that most closely matches the *KMACHINE* and `LINUX_KERNEL_TYPE` values passed in from the recipe, and use the first description they find that matches both. This is referred to as the *discovered* BSP description.

For a discovered BSP description, the tools deliberately do **not** apply the `patch` directives reachable from it, either directly or through any files it includes. The kernel source branch you are building (*KBRANCH*) is assumed to

already contain those commits as part of its history, so re-applying them would fail. Configuration fragments (`kconf` directives) are always applied. In other words, a discovered BSP contributes *configuration*, not *patches*.

This is why a recipe-space BSP description must be delivered as a `type=kmeta` directory rather than as an individual `file://*.scc` entry on `SRC_URI` (see the "[Recipe-Space Metadata](#)" section). To have your description discovered, place it in a `type=kmeta` directory and set `KMACHINE` so the tools locate it:

```
KMACHINE:myplatform ?= "myplatform"

SRC_URI:append:myplatform = " \
    file://myplatform;type=kmeta;destsuffix=myplatform \
"
```

Here, the `myplatform` directory contains the BSP description (for example `myplatform-standard.scc`, beginning with `define KMACHINE myplatform` and `define KTYPE standard`). Because the description is discovered rather than supplied as a fragment, its `patch` directives, and those of everything it includes, are inhibited, while its configuration is still applied.

If your BSP genuinely lives outside the kernel source history (the branch you build does **not** already contain the BSP commits, and the patches *must* be applied), the BSP description can opt back in to patch application by adding the following directive to the description itself:

```
define KMETA_EXTERNAL_BSP 1
```

With that directive present, the discovered BSP description is also injected into the patch phase and its `patch` directives are applied.

### 9.3.5 Organizing Your Source

Many recipes based on the `linux-yocto-custom.bb` recipe use Linux kernel sources that have only a single branch. This type of repository structure is fine for linear development supporting a single machine and architecture. However, if you work with multiple boards and architectures, a kernel source repository with multiple branches is more efficient. For example, suppose you need a series of patches for one board to boot. Sometimes, these patches are works-in-progress or fundamentally wrong, yet they are still necessary for specific boards. In these situations, you most likely do not want to include these patches in every kernel you build (i.e. have the patches as part of the default branch). It is situations like these that give rise to multiple branches used within a Linux kernel sources Git repository.

Here are repository organization strategies maximizing source reuse, removing redundancy, and logically ordering your changes. This section presents strategies for the following cases:

- Encapsulating patches in a feature description and only including the patches in the BSP descriptions of the applicable boards.
- Creating a machine branch in your kernel source repository and applying the patches on that branch only.
- Creating a feature branch in your kernel source repository and merging that branch into your BSP when needed.

The approach you take is entirely up to you and depends on what works best for your development model.

## Encapsulating Patches

If you are reusing patches from an external tree and are not working on the patches, you might find the encapsulated feature to be appropriate. Given this scenario, you do not need to create any branches in the source repository. Rather, you just take the static patches you need and encapsulate them within a feature description. Once you have the feature description, you simply include that into the BSP description as described in the "*BSP Descriptions*" section.

You can find information on how to create patches and BSP descriptions in the "*Patches*" and "*BSP Descriptions*" sections.

## Machine Branches

When you have multiple machines and architectures to support, or you are actively working on board support, it is more efficient to create branches in the repository based on individual machines. Having machine branches allows common source to remain in the development branch with any features specific to a machine stored in the appropriate machine branch. This organization method frees you from continually reintegrating your patches into a feature.

Once you have a new branch, you can set up your kernel Metadata to use the branch a couple different ways. In the recipe, you can specify the new branch as the *KBRANCH* to use for the board as follows:

```
KBRANCH = "mynewbranch"
```

Another method is to use the `branch` command in the BSP description:

```
mybsp.scc:
    define KMACHINE mybsp
    define KTYPE standard
    define KARCH i386
    include standard.scc

    branch mynewbranch

    include mybsp-hw.scc
```

If you find yourself with numerous branches, you might consider using a hierarchical branching system similar to what the Yocto Linux Kernel Git repositories use:

```
common/kernel_type/machine
```

If you had two kernel types, "standard" and "small" for instance, three machines, and common as `mydir`, the branches in your Git repository might look like this:

```
mydir/base
mydir/standard/base
mydir/standard/machine_a
mydir/standard/machine_b
mydir/standard/machine_c
```

(continues on next page)

(continua dalla pagina precedente)

```
mydir/small/base
mydir/small/machine_a
```

This organization can help clarify the branch relationships. In this case, `mydir/standard/machine_a` includes everything in `mydir/base` and `mydir/standard/base`. The "standard" and "small" branches add sources specific to those kernel types that for whatever reason are not appropriate for the other branches.

**i Nota**

The "base" branches are an artifact of the way Git manages its data internally on the filesystem: Git will not allow you to use `mydir/standard` and `mydir/standard/machine_a` because it would have to create a file and a directory named "standard".

## Feature Branches

When you are actively developing new features, it can be more efficient to work with that feature as a branch, rather than as a set of patches that have to be regularly updated. The Yocto Project Linux kernel tools provide for this with the `git merge` command.

To merge a feature branch into a BSP, insert the `git merge` command after any `branch` commands:

```
mybsp.scc:
    define KMACHINE mybsp
    define KTYPE standard
    define KARCH i386
    include standard.scc

    branch mynewbranch
    git merge myfeature

    include mybsp-hw.scc
```

### 9.3.6 SCC Description File Reference

This section provides a brief reference for the commands you can use within an SCC description file (`.scc`):

- `branch [ref]`: Creates a new branch relative to the current branch (typically `${KTYPE}`) using the currently checked-out branch, or "ref" if specified.
- `define`: Defines variables, such as *KMACHINE*, *KTYPE*, *KARCH*, and *KFEATURE\_DESCRIPTION*.
- `include SCC_FILE`: Includes an SCC file in the current file. The file is parsed as if you had inserted it inline.
- `kconf [hardware|non-hardware] CFG_FILE`: Queues a configuration fragment for merging into the final Linux `.config` file.
- `git merge GIT_BRANCH`: Merges the feature branch into the current branch.
- `patch PATCH_FILE`: Applies the patch to the current Git branch.

## 9.4 Advanced Kernel Concepts

### 9.4.1 Yocto Project Kernel Development and Maintenance

Kernels available through the Yocto Project (Yocto Linux kernels), like other kernels, are based off the Linux kernel releases from <https://www.kernel.org>. At the beginning of a major Linux kernel development cycle, the Yocto Project team chooses a Linux kernel based on factors such as release timing, the anticipated release timing of final upstream `kernel.org` versions, and Yocto Project feature requirements. Typically, the Linux kernel chosen is in the final stages of development by the Linux community. In other words, the Linux kernel is in the release candidate or "rc" phase and has yet to reach final release. But, by being in the final stages of external development, the team knows that the `kernel.org` final release will clearly be within the early stages of the Yocto Project development window.

This balance allows the Yocto Project team to deliver the most up-to-date Yocto Linux kernel possible, while still ensuring that the team has a stable official release for the baseline Linux kernel version.

As implied earlier, the ultimate source for Yocto Linux kernels are released kernels from `kernel.org`. In addition to a foundational kernel from `kernel.org`, the available Yocto Linux kernels contain a mix of important new mainline developments, non-mainline developments (when no alternative exists), Board Support Package (BSP) developments, and custom features. These additions result in a commercially released Yocto Project Linux kernel that caters to specific embedded designer needs for targeted hardware.

You can find a web interface to the Yocto Linux kernels in the *I Repository del Codice Sorgente di Yocto Project* at <https://git.yoctoproject.org/>. If you look at the interface, you will see to the left a grouping of Git repositories titled "Yocto Linux Kernel". Within this group, you will find several Linux Yocto kernels developed and included with Yocto Project releases:

- *linux-yocto-4.1*: The stable Yocto Project kernel to use with the Yocto Project Release 2.0. This kernel is based on the Linux 4.1 released kernel.
- *linux-yocto-4.4*: The stable Yocto Project kernel to use with the Yocto Project Release 2.1. This kernel is based on the Linux 4.4 released kernel.
- *linux-yocto-4.6*: A temporary kernel that is not tied to any Yocto Project release.
- *linux-yocto-4.8*: The stable yocto Project kernel to use with the Yocto Project Release 2.2.
- *linux-yocto-4.9*: The stable Yocto Project kernel to use with the Yocto Project Release 2.3. This kernel is based on the Linux 4.9 released kernel.
- *linux-yocto-4.10*: The default stable Yocto Project kernel to use with the Yocto Project Release 2.3. This kernel is based on the Linux 4.10 released kernel.
- *linux-yocto-4.12*: The default stable Yocto Project kernel to use with the Yocto Project Release 2.4. This kernel is based on the Linux 4.12 released kernel.
- *yocto-kernel-cache*: The `linux-yocto-cache` contains patches and configurations for the linux-yocto kernel tree. This repository is useful when working on the linux-yocto kernel. For more information on this "Advanced Kernel Metadata", see the "*Working with Advanced Metadata (yocto-kernel-cache)*" Chapter.
- *linux-yocto-dev*: A development kernel based on the latest upstream release candidate available.

Once a Yocto Linux kernel is officially released, the Yocto Project team goes into their next development cycle, or upward revision (uprev) cycle, while still continuing maintenance on the released kernel. It is important to note that

the most sustainable and stable way to include feature development upstream is through a kernel uprev process. Back-porting hundreds of individual fixes and minor features from various kernel versions is not sustainable and can easily compromise quality.

During the uprev cycle, the Yocto Project team uses an ongoing analysis of Linux kernel development, BSP support, and release timing to select the best possible `kernel.org` Linux kernel version on which to base subsequent Yocto Linux kernel development. The team continually monitors Linux community kernel development to look for significant features of interest. The team does consider back-porting large features if they have a significant advantage. User or community demand can also trigger a back-port or creation of new functionality in the Yocto Project baseline kernel during the uprev cycle.

Generally speaking, every new Linux kernel both adds features and introduces new bugs. These consequences are the basic properties of upstream Linux kernel development and are managed by the Yocto Project team's Yocto Linux kernel development strategy. It is the Yocto Project team's policy to not back-port minor features to the released Yocto Linux kernel. They only consider back-porting significant technological jumps --- and, that is done after a complete gap analysis. The reason for this policy is that back-porting any small to medium sized change from an evolving Linux kernel can easily create mismatches, incompatibilities and very subtle errors.

The policies described in this section result in both a stable and a cutting edge Yocto Linux kernel that mixes forward ports of existing Linux kernel features and significant and critical new functionality. Forward porting Linux kernel functionality into the Yocto Linux kernels available through the Yocto Project can be thought of as a "micro uprev". The many "micro uprevs" produce a Yocto Linux kernel version with a mix of important new mainline, non-mainline, BSP developments and feature integrations. This Yocto Linux kernel gives insight into new features and allows focused amounts of testing to be done on the kernel, which prevents surprises when selecting the next major uprev. The quality of these cutting edge Yocto Linux kernels is evolving and the kernels are used in leading edge feature and BSP development.

## 9.4.2 Yocto Linux Kernel Architecture and Branching Strategies

As mentioned earlier, a key goal of the Yocto Project is to present the developer with a kernel that has a clear and continuous history that is visible to the user. The architecture and mechanisms, in particular the branching strategies, used achieve that goal in a manner similar to upstream Linux kernel development in `kernel.org`.

You can think of a Yocto Linux kernel as consisting of a baseline Linux kernel with added features logically structured on top of the baseline. The features are tagged and organized by way of a branching strategy implemented by the Yocto Project team using the Source Code Manager (SCM) Git.

### Nota

- Git is the obvious SCM for meeting the Yocto Linux kernel organizational and structural goals described in this section. Not only is Git the SCM for Linux kernel development in `kernel.org` but, Git continues to grow in popularity and supports many different work flows, front-ends and management techniques.
- You can find documentation on Git at <https://git-scm.com/doc>. You can also get an introduction to Git as it applies to the Yocto Project in the "*Git*" section in the Yocto Project Overview and Concepts Manual. The latter reference provides an overview of Git and presents a minimal set of Git commands that allows you to be functional using Git. You can use as much, or as little, of what Git has to offer to accomplish what you need for your project. You do not have to be a "Git Expert" in order to use it with the Yocto Project.



Using Git's tagging and branching features, the Yocto Project team creates kernel branches at points where functionality is no longer shared and thus, needs to be isolated. For example, board-specific incompatibilities would require different functionality and would require a branch to separate the features. Likewise, for specific kernel features, the same branching strategy is used.

This "tree-like" architecture results in a structure that has features organized to be specific for particular functionality, single kernel types, or a subset of kernel types. Thus, the user has the ability to see the added features and the commits that make up those features. In addition to being able to see added features, the user can also view the history of what made up the baseline Linux kernel.

Another consequence of this strategy results in not having to store the same feature twice internally in the tree. Rather, the kernel team stores the unique differences required to apply the feature onto the kernel type in question.


**i Nota**

The Yocto Project team strives to place features in the tree such that features can be shared by all boards and kernel types where possible. However, during development cycles or when large features are merged, the team cannot always follow this practice. In those cases, the team uses isolated branches to merge features.

BSP-specific code additions are handled in a similar manner to kernel-specific additions. Some BSPs only make sense given certain kernel types. So, for these types, the team creates branches off the end of that kernel type for all of the BSPs that are supported on that kernel type. From the perspective of the tools that create the BSP branch, the BSP is really no different than a feature. Consequently, the same branching strategy applies to BSPs as it does to kernel features. So again, rather than store the BSP twice, the team only stores the unique differences for the BSP across the supported multiple kernels.

While this strategy can result in a tree with a significant number of branches, it is important to realize that from the developer's point of view, there is a linear path that travels from the baseline `kernel.org`, through a select group of features and ends with their BSP-specific commits. In other words, the divisions of the kernel are transparent and are not relevant to the developer on a day-to-day basis. From the developer's perspective, this path is the development branch. The developer does not need to be aware of the existence of any other branches at all. Of course, it can make sense to have these branches in the tree, should a person decide to explore them. For example, a comparison between two BSPs at either the commit level or at the line-by-line code `diff` level is now a trivial operation.

The following illustration shows the conceptual Yocto Linux kernel.



In the illustration, the "Kernel.org Branch Point" marks the specific spot (or Linux kernel release) from which the Yocto Linux kernel is created. From this point forward in the tree, features and differences are organized and tagged.

The "Yocto Project Baseline Kernel" contains functionality that is common to every kernel type and BSP that is organized further along in the tree. Placing these common features in the tree this way means features do not have to be duplicated along individual branches of the tree structure.

From the "Yocto Project Baseline Kernel", branch points represent specific functionality for individual Board Support Packages (BSPs) as well as real-time kernels. The illustration represents this through three BSP-specific branches and a real-time kernel branch. Each branch represents some unique functionality for the BSP or for a real-time Yocto Linux kernel.

In this example structure, the "Real-time (rt) Kernel" branch has common features for all real-time Yocto Linux kernels and contains more branches for individual BSP-specific real-time kernels. The illustration shows three branches as an example. Each branch points the way to specific, unique features for a respective real-time kernel as they apply to a given BSP.

The resulting tree structure presents a clear path of markers (or branches) to the developer that, for all practical

purposes, is the Yocto Linux kernel needed for any given set of requirements.

#### **Nota**

Keep in mind the figure does not take into account all the supported Yocto Linux kernels, but rather shows a single generic kernel just for conceptual purposes. Also keep in mind that this structure represents the *1 Repository del Codice Sorgente di Yocto Project* that are either pulled from during the build or established on the host development system prior to the build by either cloning a particular kernel's Git repository or by downloading and unpacking a tarball.

Working with the kernel as a structured tree follows recognized community best practices. In particular, the kernel as shipped with the product, should be considered an "upstream source" and viewed as a series of historical and documented modifications (commits). These modifications represent the development and stabilization done by the Yocto Project kernel development team.

Because commits only change at significant release points in the product life cycle, developers can work on a branch created from the last relevant commit in the shipped Yocto Project Linux kernel. As mentioned previously, the structure is transparent to the developer because the kernel tree is left in this state after cloning and building the kernel.

### 9.4.3 Kernel Build File Hierarchy


Upstream storage of all the available kernel source code is one thing, while representing and using the code on your host development system is another. Conceptually, you can think of the kernel source repositories as all the source files necessary for all the supported Yocto Linux kernels. As a developer, you are just interested in the source files for the kernel on which you are working. And, furthermore, you need them available on your host system.

Kernel source code is available on your host system several different ways:

- *Files Accessed While using devtool:* `devtool`, which is available with the Yocto Project, is the preferred method by which to modify the kernel. See the "*Kernel Modification Workflow*" section.
- *Cloned Repository:* If you are working in the kernel all the time, you probably would want to set up your own local Git repository of the Yocto Linux kernel tree. For information on how to clone a Yocto Linux kernel Git repository, see the "*Preparazione dell'Host di Build per Lavorare sul Kernel*." section.
- *Temporary Source Files from a Build:* If you just need to make some patches to the kernel using a traditional BitBake workflow (i.e. not using the `devtool`), you can access temporary kernel source files that were extracted and used during a kernel build.

The temporary kernel source files resulting from a build using BitBake have a particular hierarchy. When you build the kernel on your development system, all files needed for the build are taken from the source repositories pointed to by the `SRC_URI` variable and gathered in a temporary work area where they are subsequently used to create the unique kernel. Thus, in a sense, the process constructs a local source tree specific to your kernel from which to generate the new kernel image.

The following figure shows the temporary file structure created on your host system when you build the kernel using BitBake. This *Build Directory* contains all the source files used during the build.



Again, for additional information on the Yocto Project kernel's architecture and its branching strategy, see the "[Yocto Linux Kernel Architecture and Branching Strategies](#)" section. You can also reference the "[Using devtool to Patch the Kernel](#)" and "[Using Traditional Kernel Development to Patch the Kernel](#)" sections for detailed example that modifies the kernel.

#### 9.4.4 Determining Hardware and Non-Hardware Features for the Kernel Configuration Audit Phase

This section describes part of the kernel configuration audit phase that most developers can ignore. For general information on kernel configuration including `menuconfig`, `defconfig` files, and configuration fragments, see the "[Configuring the Kernel](#)" section.

During this part of the audit phase, the contents of the final `.config` file are compared against the fragments specified by the system. These fragments can be system fragments, distro fragments, or user-specified configuration elements. Regardless of their origin, the OpenEmbedded build system warns the user if a specific option is not included in the final kernel configuration.

By default, in order to not overwhelm the user with configuration warnings, the system only reports missing "hardware" options as they could result in a boot failure or indicate that important hardware is not available.

To determine whether or not a given option is "hardware" or "non-hardware", the kernel Metadata in `yocto-kernel-cache` contains files that classify individual or groups of options as either hardware or non-hardware. To better show this, consider a situation where the `yocto-kernel-cache` contains the following files:

```

yocto-kernel-cache/features/drm-psb/hardware.cfg
yocto-kernel-cache/features/kgdb/hardware.cfg
yocto-kernel-cache/ktypes/base/hardware.cfg
yocto-kernel-cache/bsp/mti-malta32/hardware.cfg
yocto-kernel-cache/bsp/qemu-ppc32/hardware.cfg
  
```

(continues on next page)

(continua dalla pagina precedente)

```

yocto-kernel-cache/bsp/qemuarmv8/hardware.cfg
yocto-kernel-cache/bsp/mti-malta64/hardware.cfg
yocto-kernel-cache/bsp/arm-versatile-926ejs/hardware.cfg
yocto-kernel-cache/bsp/common-pc/hardware.cfg
yocto-kernel-cache/bsp/common-pc-64/hardware.cfg
yocto-kernel-cache/features/rfkill/non-hardware.cfg
yocto-kernel-cache/ktypes/base/non-hardware.cfg
yocto-kernel-cache/features/aufs/non-hardware.kcf
yocto-kernel-cache/features/ocf/non-hardware.kcf
yocto-kernel-cache/ktypes/base/non-hardware.kcf
yocto-kernel-cache/ktypes/base/hardware.kcf
yocto-kernel-cache/bsp/qemu-ppc32/hardware.kcf

```

Here are explanations for the various files:

- `hardware.kcf`: Specifies a list of kernel Kconfig files that contain hardware options only.
- `non-hardware.kcf`: Specifies a list of kernel Kconfig files that contain non-hardware options only.
- `hardware.cfg`: Specifies a list of kernel `CONFIG_` options that are hardware, regardless of whether or not they are within a Kconfig file specified by a hardware or non-hardware Kconfig file (i.e. `hardware.kcf` or `non-hardware.kcf`).
- `non-hardware.cfg`: Specifies a list of kernel `CONFIG_` options that are not hardware, regardless of whether or not they are within a Kconfig file specified by a hardware or non-hardware Kconfig file (i.e. `hardware.kcf` or `non-hardware.kcf`).

Here is a specific example using the `kernel-cache/bsp/mti-malta32/hardware.cfg`:

```

CONFIG_SERIAL_8250
CONFIG_SERIAL_8250_CONSOLE
CONFIG_SERIAL_8250_NR_UARTS
CONFIG_SERIAL_8250_PCI
CONFIG_SERIAL_CORE
CONFIG_SERIAL_CORE_CONSOLE
CONFIG_VGA_ARB

```

The kernel configuration audit automatically detects these files (hence the names must be exactly the ones discussed here), and uses them as inputs when generating warnings about the final `.config` file.

A user-specified kernel Metadata repository, or recipe space feature, can use these same files to classify options that are found within its `.cfg` files as hardware or non-hardware, to prevent the OpenEmbedded build system from producing an error or warning when an option is not in the final `.config` file.

## 9.5 Kernel Maintenance

### 9.5.1 Tree Construction

This section describes construction of the Yocto Project kernel source repositories as accomplished by the Yocto Project team to create Yocto Linux kernel repositories. These kernel repositories are found under the heading "Yocto Linux Kernel" at <https://git.yoctoproject.org/> and are shipped as part of a Yocto Project release. The team creates these repositories by compiling and executing the set of feature descriptions for every BSP and feature in the product. Those feature descriptions list all necessary patches, configurations, branches, tags, and feature divisions found in a Yocto Linux kernel. Thus, the Yocto Project Linux kernel repository (or tree) and accompanying Metadata in the `yocto-kernel-cache` are built.

The existence of these repositories allow you to access and clone a particular Yocto Project Linux kernel repository and use it to build images based on their configurations and features.

You can find the files used to describe all the valid features and BSPs in the Yocto Project Linux kernel in any clone of the Yocto Project Linux kernel source repository and `yocto-kernel-cache` Git trees. For example, the following commands clone the Yocto Project baseline Linux kernel that branches off `linux.org` version 4.12 and the `yocto-kernel-cache`, which contains stores of kernel Metadata:

```
$ git clone https://git.yoctoproject.org/linux-yocto-4.12
$ git clone https://git.yoctoproject.org/linux-kernel-cache
```

For more information on how to set up a local Git repository of the Yocto Project Linux kernel files, see the *"Preparazione dell'Host di Build per Lavorare sul Kernel."* section.

Once you have cloned the kernel Git repository and the cache of Metadata on your local machine, you can discover the branches that are available in the repository using the following Git command:

```
$ git branch -a
```

Checking out a branch allows you to work with a particular Yocto Linux kernel. For example, the following commands check out the "standard/beagleboard" branch of the Yocto Linux kernel repository and the "yocto-4.12" branch of the `yocto-kernel-cache` repository:

```
$ cd ~/linux-yocto-4.12
$ git checkout -b my-kernel-4.12 remotes/origin/standard/beagleboard
$ cd ~/linux-kernel-cache
$ git checkout -b my-4.12-metadata remotes/origin/yocto-4.12
```

#### Nota

Branches in the `yocto-kernel-cache` repository correspond to Yocto Linux kernel versions (e.g. "yocto-4.12", "yocto-4.10", "yocto-4.9", and so forth).

Once you have checked out and switched to appropriate branches, you can see a snapshot of all the kernel source files used to build that particular Yocto Linux kernel for a particular board.

To see the features and configurations for a particular Yocto Linux kernel, you need to examine the `yocto-kernel-cache` Git repository. As mentioned, branches in the `yocto-kernel-cache` repository correspond to Yocto Linux kernel versions (e.g. `yocto-4.12`). Branches contain descriptions in the form of `.scc` and `.cfg` files.

You should realize, however, that browsing your local `yocto-kernel-cache` repository for feature descriptions and patches is not an effective way to determine what is in a particular kernel branch. Instead, you should use Git directly to discover the changes in a branch. Using Git is an efficient and flexible way to inspect changes to the kernel.

#### Nota

Ground up reconstruction of the complete kernel tree is an action only taken by the Yocto Project team during an active development cycle. When you create a clone of the kernel Git repository, you are simply making it efficiently available for building and development.

The following steps describe what happens when the Yocto Project Team constructs the Yocto Project kernel source Git repository (or tree) found at <https://git.yoctoproject.org/> given the introduction of a new top-level kernel feature or BSP. The following actions effectively provide the Metadata and create the tree that includes the new feature, patch, or BSP:

1. *Pass Feature to the OpenEmbedded Build System:* A top-level kernel feature is passed to the kernel build subsystem. Normally, this feature is a BSP for a particular kernel type.
2. *Locate Feature:* The file that describes the top-level feature is located by searching these system directories:
  - The in-tree kernel-cache directories, which are located in the `yocto-kernel-cache` repository organized under the "Yocto Linux Kernel" heading in the [Yocto Project Source Repositories](#).
  - Areas pointed to by `SRC_URI` statements found in kernel recipes.

For a typical build, the target of the search is a feature description in an `.scc` file whose name follows this format (e.g. `beaglebone-standard.scc` and `beaglebone-preempt-rt.scc`):

```
bsp_root_name-kernel_type.scc
```

3. *Expand Feature:* Once located, the feature description is either expanded into a simple script of actions, or into an existing equivalent script that is already part of the shipped kernel.
4. *Append Extra Features:* Extra features are appended to the top-level feature description. These features can come from the `KERNEL_FEATURES` variable in recipes.
5. *Locate, Expand, and Append Each Feature:* Each extra feature is located, expanded and appended to the script as described in step three.
6. *Execute the Script:* The script is executed to produce files `.scc` and `.cfg` files in appropriate directories of the `yocto-kernel-cache` repository. These files are descriptions of all the branches, tags, patches and configurations that need to be applied to the base Git repository to completely create the source (build) branch for the new BSP or feature.
7. *Clone Base Repository:* The base repository is cloned, and the actions listed in the `yocto-kernel-cache` directories are applied to the tree.

8. *Perform Cleanup*: The Git repositories are left with the desired branches checked out and any required branching, patching and tagging has been performed.

The kernel tree and cache are ready for developer consumption to be locally cloned, configured, and built into a Yocto Project kernel specific to some target hardware.

#### Nota

- The generated `yocto-kernel-cache` repository adds to the kernel as shipped with the Yocto Project release. Any add-ons and configuration data are applied to the end of an existing branch. The full repository generation that is found in the official Yocto Project kernel repositories at <https://git.yoctoproject.org/> is the combination of all supported boards and configurations.
- The technique the Yocto Project team uses is flexible and allows for seamless blending of an immutable history with additional patches specific to a deployment. Any additions to the kernel become an integrated part of the branches.
- The full kernel tree that you see on <https://git.yoctoproject.org/> is generated through repeating the above steps for all valid BSPs. The end result is a branched, clean history tree that makes up the kernel for a given release. You can see the script (`kgit-scc`) responsible for this in the `yocto-kernel-tools` repository.
- The steps used to construct the full kernel tree are the same steps that BitBake uses when it builds a kernel image.

## 9.5.2 Build Strategy

Once you have cloned a Yocto Linux kernel repository and the cache repository (`yocto-kernel-cache`) onto your development system, you can consider the compilation phase of kernel development, which is building a kernel image. Some prerequisites are validated by the build process before compilation starts:

- The `SRC_URI` points to the kernel Git repository.
- A BSP build branch with Metadata exists in the `yocto-kernel-cache` repository. The branch is based on the Yocto Linux kernel version and has configurations and features grouped under the `yocto-kernel-cache/bsp` directory. For example, features and configurations for the BeagleBone Board assuming a `linux-yocto_4.12` kernel reside in the following area of the `yocto-kernel-cache` repository: `yocto-kernel-cache/bsp/beaglebone`

#### Nota

In the previous example, the "yocto-4.12" branch is checked out in the `yocto-kernel-cache` repository.

The OpenEmbedded build system makes sure these conditions are satisfied before attempting compilation. Other means, however, do exist, such as bootstrapping a BSP.

Before building a kernel, the build process verifies the tree and configures the kernel by processing all of the configuration "fragments" specified by feature descriptions in the `.scc` files. As the features are compiled, associated kernel configuration fragments are noted and recorded in the series of directories in their compilation order. The fragments are migrated, pre-processed and passed to the Linux Kernel Configuration subsystem (`lkc`) as raw input



in the form of a `.config` file. The `lkc` uses its own internal dependency constraints to do the final processing of that information and generates the final `.config` file that is used during compilation.

Using the board's architecture and other relevant values from the board's template, kernel compilation is started and a kernel image is produced.

The other thing that you notice once you configure a kernel is that the build process generates a build tree that is separate from your kernel's local Git source repository tree. This build tree has a name that uses the following form, where `${MACHINE}` is the metadata name of the machine (BSP) and "kernel\_type" is one of the Yocto Project supported kernel types (e.g. "standard"):

```
linux-${MACHINE}-kernel_type-build
```

The existing support in the `kernel.org` tree achieves this default functionality.

This behavior means that all the generated files for a particular machine or BSP are now in the build tree directory. The files include the final `.config` file, all the `.o` files, the `.a` files, and so forth. Since each machine or BSP has its own separate *Build Directory* in its own separate branch of the Git repository, you can easily switch between different builds.

## 9.6 Kernel Development FAQ

### 9.6.1 Common Questions and Solutions

Here are some solutions for common questions.

#### How do I use my own Linux kernel `.config` file?

Refer to the "*Changing the Configuration*" section for information.

#### How do I create configuration fragments?

A: Refer to the "*Creating Configuration Fragments*" section for information.

#### How do I use my own Linux kernel sources?

Refer to the "*Working With Your Own Sources*" section for information.

#### How do I install/not-install the kernel image on the root filesystem?

The kernel image (e.g. `vmlinuz`) is provided by the `kernel-image` package. Image recipes depend on `kernel-base`. To specify whether or not the kernel image is installed in the generated root filesystem, override `RRECOMMENDS:${KERNEL_PACKAGE_NAME}-base` to include or not include "kernel-image". See the "*Appending Other Layers Metadata With Your Layer*" section in the Yocto Project Development Tasks Manual for information on how to use an append file to override metadata.

## How do I install a specific kernel module?

Linux kernel modules are packaged individually. To ensure a specific kernel module is included in an image, include it in the appropriate machine *RRECOMMENDS* variable. These other variables are useful for installing specific modules: - *MACHINE\_ESSENTIAL\_EXTRA\_RDEPENDS* - *MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS* - *MACHINE\_EXTRA\_RDEPENDS* - *MACHINE\_EXTRA\_RRECOMMENDS*

For example, set the following in the `qemux86.conf` file to include the `ab123` kernel modules with images built for the `qemux86` machine:

```
MACHINE_EXTRA_RRECOMMENDS += "kernel-module-ab123"
```

For more information, see the "*Incorporating Out-of-Tree Modules*" section.

## How do I change the Linux kernel command line?

The Linux kernel command line is typically specified in the machine config using the *APPEND* variable. For example, you can add some helpful debug information doing the following:

```
APPEND += "printk.time=y initcall_debug debug"
```

The Yocto Project ®

<docs@lists.yoctoproject.org>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo `docs@lists.yoctoproject.org` o di accedere su [Libera Chat](#) al canale `#yocto`.

---

## Manuale di Sicurezza di Yocto Project

---

### 10.1 Introduzione

Benvenuti nel Manuale di Sicurezza di Yocto Project. Questo manuale fornisce le procedure pertinenti per la gestione delle attività di sicurezza supportate nell'ambiente di Yocto Project. Il manuale raggruppa le procedure correlate in sezioni di livello superiore. Le procedure possono essere composte da passaggi di alto o basso livello, a seconda dell'argomento.

Questo manuale fornisce quanto segue:

- Procedure che consentono di proteggere un'immagine utilizzando le funzionalità supportate da Yocto Project; ad esempio, rendere un filesystem root di sola lettura [read-only].
- Procedure relative a processi esterni alle immagini target; ad esempio, come gestire le vulnerabilità.

Questo manuale non fornisce quanto segue:

- Procedure per funzionalità di sicurezza implementate al di fuori di *OpenEmbedded-Core (OE-Core)*.
- Documentazione relativa ai meccanismi di sicurezza stessi, che spesso si trova nella documentazione della funzionalità stessa. Questo manuale si concentra su come integrare tali meccanismi di sicurezza all'interno di Yocto Project.

## 10.2 Sicurezza del Processo di Build

*OpenEmbedded Build System* viene utilizzato per eseguire le compilazioni e la sua progettazione è stata attentamente studiata per garantire sicurezza e riproducibilità. Come qualsiasi sistema, è necessario utilizzarlo con attenzione e in conformità con la sua progettazione affinché ciò sia possibile. Gli utenti del sistema devono tenere presente quanto segue:

- In generale, ogni input del processo di build viene verificato in qualche modo. Per i file tarball del codice sorgente, viene generato un checksum. Gli alberi di codice sorgente Git hanno una specifica revisione Git. Anche i metadati sono solitamente gestiti tramite controllo di versione e presentano delle revisioni.

Per ulteriori informazioni, consultare la sezione [File Download Support](#) del Manuale Utente di BitBake.

- Alcuni elementi che possono influenzare la compilazione non vengono verificati. Si presume che il sistema operativo in esecuzione sia sicuro e di versione nota. Il sistema adotta misure significative per isolare l'output da eventuali contaminazioni provenienti dall'host, ma ciò è certamente possibile, soprattutto in modo malevolo.

Per ulteriori informazioni sulle distribuzioni host supportate, consultare la sezione [Distribuzioni Linux Supportate](#) del Manuale di Riferimento di Yocto Project.

- Le build presuppongono che *DL\_DIR* sia una posizione sicura. Una volta che gli artefatti scaricati entrano in tale posizione, non vengono ri-verificati ripetutamente. Un utente potrebbe modificare gli alberi Git o i file tar presenti in quella posizione in modi che la build potrebbe non rilevare.
- Le build presuppongono che gli oggetti sstate provenienti da *SSTATE\_DIR* o da un *sstate mirror* configurato siano sicuri (con *signature checks* se configurati).
- Lo strumento di build principale, *BitBake*, è un motore di esecuzione ed esegue codice sia durante la compilazione che durante l'analisi delle ricette. Questo non rappresenta un problema di sicurezza, bensì una parte essenziale della sua funzione e del suo scopo.
- *OpenEmbedded-Core (OE-Core)* è stato ampiamente testato per la riproducibilità dei problemi, ma altri layer, le relative ricette e il codice potrebbero non essere stati testati altrettanto a fondo. Tali test di riproducibilità sono a disposizione di chiunque desideri eseguirli sui propri layer e sul proprio codice.
- Le build combinano molti componenti software diversi e ci si basa sul presupposto che non vi siano problemi nelle relative codebase. Raccomandiamo di configurare gli ambienti di compilazione in modo tale che, qualora venisse scoperto un problema di questo tipo (cosa che potrebbe accadere in futuro), gli ambienti stessi possano essere semplicemente eliminati e ricostruiti da zero, ovvero siano "usa e getta".

## 10.3 Come Rendere le Immagini più Sicure

Quando la sicurezza di un'immagine è una priorità, esistono passaggi, strumenti e variabili da considerare per raggiungere gli obiettivi di sicurezza necessari per il proprio dispositivo. Non tutte le situazioni sono identiche quando si tratta di proteggere un'immagine. Pertanto, questa sezione fornisce alcune indicazioni e suggerimenti da tenere in considerazione quando si desidera rendere la propria immagine più sicura.

**i Nota**

Poiché i requisiti e i rischi per la sicurezza variano a seconda del tipo di dispositivo, questa sezione non può fornire un riferimento completo sulla protezione del proprio sistema operativo personalizzato. Si raccomanda vivamente di consultare anche altre fonti di informazione sulla protezione dei sistemi Linux embedded e sulla sicurezza in generale.

### 10.3.1 Considerazioni Generali

Esistono considerazioni generali che possono aiutare a creare immagini più sicure. Per rendere il dispositivo più sicuro, si devono tenere in considerazione i seguenti suggerimenti:

- Analizzare [scan] il codice aggiuntivo che si sta inserendo nel sistema (ad esempio, il codice dell'applicazione) utilizzando strumenti di analisi statica. Cercare buffer overflow e altri potenziali problemi di sicurezza.
- Prestare particolare attenzione alla sicurezza di qualsiasi interfaccia di amministrazione basata sul web.

Le interfacce web in genere devono svolgere funzioni amministrative e tendono a richiedere privilegi elevati. Pertanto, le conseguenze derivanti da una compromissione della sicurezza dell'interfaccia possono essere gravi. Cerca vulnerabilità web comuni come cross-site scripting (XSS), input non validati e così via.

Come per le password di sistema, le credenziali di default per accedere a un'interfaccia basata sul web non dovrebbero essere le stesse su tutti i dispositivi. Questo è particolarmente vero se l'interfaccia è abilitata di default, poiché si può presumere che molti utenti finali non modificheranno le credenziali.

- Si deve poter aggiornare il software sul dispositivo per mitigare le vulnerabilità che potrebbero essere scoperte in futuro. Questa considerazione è particolarmente importante quando il dispositivo è connesso alla rete.
- Eseguire regolarmente scansioni e applicare le correzioni per le vulnerabilità di sicurezza CVE che interessano tutti i componenti software del prodotto. Vedere "*Verifica delle Vulnerabilità*".
- Aggiornare regolarmente la versione di *BitBake* e dei layer (ad esempio *OpenEmbedded-Core (OE-Core)*, *meta-yocto*, ...), ad esempio per applicare aggiornamenti e correzioni di sicurezza dai branch stabile e *LTS*.
- Rimuovere o disabilitare la funzionalità di debug prima di generare l'immagine finale. Per informazioni su come procedere, consultare la sezione "*Considerazioni Specifiche per il Sistema di Build OpenEmbedded*".
- Non ci devono essere in ascolto servizi di rete non necessari.
- Rimuovere dall'immagine qualsiasi software non necessario.
- Abilitare il supporto hardware per la funzionalità di avvio protetto (Secure Boot) se il dispositivo la supporta.

### 10.3.2 Flag di Sicurezza

Yocto Project dispone di flag di sicurezza che è possibile abilitare per rendere più sicuro l'output della build. I flag di sicurezza si trovano nel file `meta/conf/distro/include/security_flags.inc` all'interno di *OpenEmbedded-Core (OE-Core)*.

**i Nota**

A seconda della ricetta, alcuni flag di sicurezza sono abilitati o disabilitati per impostazione predefinita.

Utilizzare la seguente riga nel file *build/conf/local.conf* o nel *configuration file* della propria distribuzione per abilitare i flag di sicurezza del compilatore e del linker per la build:

```
require conf/distro/include/security_flags.inc
```

### 10.3.3 Considerazioni Specifiche per il Sistema di Build OpenEmbedded

È possibile adottare alcune misure specifiche per il sistema di build OpenEmbedded per rendere le immagini più sicure:

- Durante lo sviluppo, è utile ridurre il livello di sicurezza delle build e consentire l'utilizzo di password vuote o accessi come root. Questo viene generalmente fatto aggiungendo i valori "allow-empty-password", "allow-root-login" e "empty-root-password" alle funzionalità dell'immagine di build, solitamente aggiungendo la riga:

```
EXTRA_IMAGE_FEATURES = "allow-empty-password empty-root-password allow-root-  
→login"
```

al *configuration file* della propria distribuzione, oppure abilitando il frammento di configurazione esattamente equivalente *core/yocto/root-login-with-empty-password*.

Se si utilizza uno di questi approcci durante lo sviluppo, si devono rimuovere o disattivare queste impostazioni prima di generare l'immagine di produzione finale.

- È possibile impostare una password di root per l'immagine e anche impostare password per eventuali utenti aggiuntivi (ad esempio, utenti amministrativi o di servizio). Quando si impostano password per più immagini o utenti, è importante non duplicarle.

Per impostare le password, utilizzare la classe *extrausers*, che è il metodo consigliato. Per un esempio su come impostare le password di root e degli utenti, consultare la sezione "*extrausers*".

**i Nota**

Quando si aggiungono ulteriori account utente o si imposta una password di root, prestare attenzione a non utilizzare la stessa password su tutti i dispositivi. In tal caso, se la password impostata viene esposta, tutti i dispositivi potrebbero essere compromessi. Se è necessario questo accesso ma si desidera garantire la sicurezza, è consigliabile impostare una password diversa e casuale per ogni dispositivo. In genere, questa operazione viene eseguita separatamente dopo aver distribuito l'immagine sul dispositivo.

- Si consiglia di abilitare un framework di controllo degli accessi obbligatorio (MAC) come SMACK o SELinux e di configurarlo in modo appropriato in base all'utilizzo del dispositivo. Maggiori informazioni nel layer *meta-selinux*.

### 10.3.4 Tool per Rafforzare la Sicurezza dell'Immagine

Yocto Project fornisce strumenti per rendere l'immagine più sicura. Si possono trovare questi strumenti nel layer `meta-security` del [Repository del Codice Sorgente di Yocto Project](#).

## 10.4 Verifica delle Vulnerabilità

### 10.4.1 Vulnerabilità in OpenEmbedded-Core (OE-Core)

Yocto Project dispone di un'infrastruttura per tracciare e risolvere le vulnerabilità di sicurezza note e non ancora corrette, monitorate dal database pubblico [Common Vulnerabilities and Exposures \(CVE\)](#).

Yocto Project mantiene un [elenco di vulnerabilità note](#) per i pacchetti di *OpenEmbedded-Core (OE-Core)*, monitorando l'evoluzione del numero di CVE non ancora corrette e lo stato delle patch. Queste informazioni sono disponibili per la versione di sviluppo corrente e per ogni release supportata.

La sicurezza è un processo, non un prodotto, e pertanto, in qualsiasi momento, diversi problemi di sicurezza potrebbero interessare *OpenEmbedded-Core (OE-Core)*. Spetta ai manutentori, agli utenti, ai collaboratori e a chiunque sia interessato ai problemi indagare e, se possibile, risolverli aggiornando i componenti software a versioni più recenti o applicando patch per correggerli. Si consiglia di collaborare con i manutentori di *OpenEmbedded-Core (OE-Core)* e di inviare patch per risolverli; per maggiori dettagli, consultare "[Apportare Modifiche a un Componente](#)".

### 10.4.2 Verifica delle vulnerabilità in fase di build

Per abilitare la verifica delle vulnerabilità di sicurezza CVE nell'immagine o nel target specifico che si sta compilando, eseguire il seguente comando dalla propria *Build Directory*:

```
$ bitbake-config-build enable-fragment core/yocto/sbom-cve-check
```

Oppure aggiungere la seguente istruzione a un *configuration file*:

```
OE_FRAGMENTS += "core/yocto/sbom-cve-check"
```

Questo abiliterà la classe *sbom-cve-check* e imporrà le impostazioni consigliate per il suo utilizzo.

Il database CVE contiene alcune voci obsolete e incomplete che sono state ritenute non rilevanti per *OpenEmbedded-Core (OE-Core)*. È possibile escludere queste voci CVE dal controllo aggiungendo la seguente istruzione:

```
include conf/distro/include/cve-extra-exclusions.inc
```

Con il frammento *core/yocto/sbom-cve-check* abilitato, la build *BitBake* di un'immagine tenterà di mappare il nome della ricetta e le informazioni sulla versione di ciascun componente software compilato al database CVE e genererà report nella directory di distribuzione (*DEPLOY\_DIR\_IMAGE*), uno dei quali è: `tmp/deploy/images/<machine>/<image-name>-<machine>.rootfs.sbom-cve-check.yocto.json`, un report contenente:

- Metadati relativi al componente software, come nomi e versioni
- Metadati relativi al problema CVE, come descrizione e collegamento NVD
- Per ogni componente software, un elenco di CVE che potrebbero avere un impatto su questa versione

- Stato di ogni CVE: Patched, Unpatched o Ignored

### Nota

Viene generato anche un altro report denominato `<image-name>-<machine>.rootfs.sbom-cve-check.spdx.json`: si tratta del file *SPDX* arricchito dell'immagine, contenente le stesse informazioni del punto precedente e molte più informazioni sui metadati relativi ai pacchetti inclusi nell'immagine. Per ulteriori informazioni su *SPDX*, consultare la sezione *Creating a Software Bill of Materials* del Manuale di Sviluppo dei Task di Yocto Project.

Ogni elemento nell'elenco "package" corrisponde a un pacchetto installato sull'immagine compilata. Ciascuno di questi pacchetti contiene un certo numero di voci CVE nella sottolista "issue". Queste CVE possono avere i seguenti stati:

- Patched significa che è stato applicato un file di patch per risolvere il problema di sicurezza.
- Unpatched significa che non sono state applicate patch per risolvere il problema e che è necessario indagare sul problema stesso.
- Ignored significa che, dopo l'analisi, si è ritenuto opportuno ignorare il problema, ad esempio perché interessa il componente software su una piattaforma di sistema operativo diversa.

Ad esempio, il report per il pacchetto `glibc` si presenta così (semplificato):

```
{
  "version": "1",
  "package": [
    {
      "name": "glibc",
      "layer": "core",
      "version": "2.43+git",
      "products": [
        {
          "product": "glibc",
          "cvesInRecord": "Yes"
        }
      ],
      "issue": [
        {
          "id": "CVE-2010-4756",
          "status": "Unpatched",
          "link": "https://nvd.nist.gov/vuln/detail/CVE-2010-4756",
          "summary": "The glob implementation in the GNU C Library (aka glibc or ↵
↵ libc6) allows remote authenticated users to cause a denial of service (CPU and ↵
↵ memory consumption) via crafted glob expressions that do not match any pathnames, ↵
↵ as demonstrated by glob expressions in STAT commands to an FTP daemon, a ↵
↵ different vulnerability than CVE-2010-2632.",
```

(continues on next page)



(continua dalla pagina precedente)

```

    "scorev2": "4.0",
    "scorev3": "0.0",
    "scorev4": "0.0",
    "modified": "2025-11-03T22:15:41.000",
    "vector": "NETWORK",
    "vectorString": "AV:N/AC:L/Au:S/C:N/I:N/A:P",
    "detail": "no-version-ranges",
    "description": "Check package version"
  },
  {
    "id": "CVE-2018-6551",
    "status": "Patched",
    "link": "https://nvd.nist.gov/vuln/detail/CVE-2018-6551",
    "summary": "The malloc implementation in the GNU C Library (aka glibc or ↵
↵libc6), from version 2.24 to 2.26 on powerpc, and only in version 2.26 on i386, ↵
↵did not properly handle malloc calls with arguments close to SIZE_MAX and could ↵
↵return a pointer to a heap region that is smaller than requested, eventually ↵
↵leading to heap corruption.",
    "scorev2": "7.5",
    "scorev3": "9.8",
    "scorev4": "0.0",
    "modified": "2024-11-21T04:10:53.000",
    "vector": "NETWORK",
    "vectorString": "CVSS:3.0/AV:N/AC:L/PR:N/UI:N/S:U/C:H/I:H/A:H",
    "detail": "version-not-in-range"
  },
  {
    "id": "CVE-2019-1010022",
    "status": "Ignored",
    "link": "https://nvd.nist.gov/vuln/detail/CVE-2019-1010022",
    "summary": "GNU Libc current is affected by: Mitigation bypass. The ↵
↵impact is: Attacker may bypass stack guard protection. The component is: nptl. ↵
↵The attack vector is: Exploit stack buffer overflow vulnerability and use this ↵
↵bypass vulnerability to bypass stack guard. NOTE: Upstream comments indicate ↵
↵"this is being treated as a non-security bug and no real threat.",
    "scorev2": "7.5",
    "scorev3": "9.8",
    "scorev4": "0.0",
    "modified": "2024-11-21T04:17:55.000",
    "vector": "NETWORK",
    "vectorString": "CVSS:3.0/AV:N/AC:L/PR:N/UI:N/S:U/C:H/I:H/A:H",
    "description": "Upstream glibc maintainers dispute there is any issue ↵
↵and have no plans to address it further. this is being treated as a non-security ↵

```

(continues on next page)

(continua dalla pagina precedente)

```

↪bug and no real threat."
    }
  ],
  "cpes": ["cpe:2.3:*:*glibc:2.43:*:*:*:*:*"]
}
]
}

```

In fase di compilazione, la classe `sbom-cve-check` genererà anche warning relativi alle CVE Unpatched CVEs (quando `SBOM_CVE_CHECK_SHOW_WARNINGS` è impostato su "1"):

```

WARNING: core-image-minimal-1.0-r0 do_sbom_cve_check: glibc-2.43+git: Found_
↪unpatched CVEs: CVE-2010-4756

```

### 10.4.3 Correzione delle mappature tra nome prodotto e versione CVE

Per default, `sbom-cve-check` utilizza il nome della ricetta `BPN` come nome prodotto CVE quando interroga il database CVE. Se questa mappatura contiene falsi positivi, ad esempio Alcune vulnerabilità CVE segnalate potrebbero non riguardare il componente software in questione, oppure potrebbero verificarsi falsi negativi, ad esempio alcune vulnerabilità CVE non risultano avere un impatto sulla ricetta quando invece dovrebbero. In questi casi, il problema potrebbe risiedere nella mappatura tra il nome della ricetta e il prodotto CVE. Questi problemi di mappatura possono essere risolti impostando la variabile `CVE_PRODUCT` all'interno della ricetta. Questa variabile definisce il nome del componente software nel database CVE NIST upstream.

La variabile supporta l'utilizzo di nomi di fornitori e prodotti come segue:

```
CVE_PRODUCT = "flex_project:flex westes:flex"
```

In questo esempio, abbiamo due possibili nomi di fornitori, `flex_project` e `westes`, con il nome del prodotto `flex`. Con questa impostazione, la ricetta `flex` viene mappata solo a questo specifico prodotto e non a prodotti di altri fornitori con lo stesso nome `flex`.

Analogamente, quando la versione della ricetta `PV` non è compatibile con le versioni del software utilizzate dalle release dei componenti software a monte e con il database CVE, è possibile risolvere il problema utilizzando la variabile `CVE_VERSION`.

Si noti che se le voci CVE nel database NVD contengono bug o informazioni mancanti o incomplete, si consiglia di correggere direttamente le informazioni nel database stesso, anziché cercare di aggirare i problemi, eventualmente per lungo tempo, nelle ricette di *OpenEmbedded-Core (OE-Core)*. È possibile fornire feedback a NVD in merito alle voci CVE tramite il [modulo di contatto NVD](#).

### 10.4.4 Correzione delle vulnerabilità nelle ricette

Supponiamo che una vulnerabilità di sicurezza CVE interessi un componente software. In tal caso, è possibile risolverla aggiornando a una versione più recente, applicando una patch o contrassegnandola come "patched" tramite il flag della variabile `CVE_STATUS`. Per i branch master di *OpenEmbedded-Core (OE-Core)*, l'aggiornamento a una

versione più recente del componente software con le correzioni è l'opzione migliore, ma è possibile applicare delle patch se le versioni non sono ancora disponibili.

Per i branch stabili, è preferibile evitare incompatibilità con le API (Application Programming Interface) o le ABI (Application Binary Interface). Quando si invia un aggiornamento, è preferibile un aggiornamento a una versione minore del componente se la versione è retrocompatibile. Molti componenti software hanno versioni stabili retrocompatibili, con un esempio notevole del kernel Linux. Tuttavia, se la nuova versione introduce o potrebbe introdurre incompatibilità, è preferibile estrarre e applicare le patch.

Ecco un esempio di come correggere le vulnerabilità di sicurezza CVE con i file di patch, tratto dalla ricetta [ffmpeg recipe per dunfell](#):

```
SRC_URI = "https://www.ffmpeg.org/releases/${BP}.tar.xz \
    file://mips64_cpu_detection.patch \
    file://CVE-2020-12284.patch \
    file://0001-libavutil-include-assembly-with-full-path-from-sourc.patch \
    file://CVE-2021-3566.patch \
    file://CVE-2021-38291.patch \
    file://CVE-2022-1475.patch \
    file://CVE-2022-3109.patch \
    file://CVE-2022-3341.patch \
    file://CVE-2022-48434.patch \
"
```

La ricetta include sia correzioni generiche che specifiche per la sicurezza. I file di patch CVE prendono il nome dalla vulnerabilità CVE che correggono.

Quando si prepara il file di patch, utilizzare la patch originale dal repository upstream. Non utilizzare patch provenienti da distribuzioni diverse, a meno che non siano l'unica fonte disponibile.

Modificare la patch aggiungendo i metadati relativi a OE. Seguiremo l'esempio della patch `CVE-2022-3341.patch`.

Il messaggio di commit originale è:

```
From 9cf652cef49d74afe3d454f27d49eb1a1394951e Mon Sep 17 00:00:00 2001
From: Jiasheng Jiang <jiasheng@iscas.ac.cn>
Date: Wed, 23 Feb 2022 10:31:59 +0800
Subject: [PATCH] avformat/nutdec: Add check for avformat_new_stream

Check for failure of avformat_new_stream() and propagate
the error code.

Signed-off-by: Michael Niedermayer <michael@niedermayer.cc>
---
 libavformat/nutdec.c | 16 ++++++-----
 1 file changed, 12 insertions(+), 4 deletions(-)
```

Per il corretto funzionamento di [sbom-cve-check](#), è necessario includere l'identificativo CVE nel tag `CVE:` del messaggio di commit del file patch, utilizzando il seguente formato:

CVE: CVE-2022-3341

È inoltre necessario aggiungere il tag `Upstream-Status:` con un link alla patch originale e la firma del team che ha lavorato al backport. Eventuali modifiche alla patch originale devono essere annotate nel tag `Comments:`.

Con queste informazioni aggiuntive, l'header del file patch in OE-core diventa:

```
From 9cf652cef49d74afe3d454f27d49eb1a1394951e Mon Sep 17 00:00:00 2001
From: Jiasheng Jiang <jiasheng@iscas.ac.cn>
Date: Wed, 23 Feb 2022 10:31:59 +0800
Subject: [PATCH] avformat/nutdec: Add check for avformat_new_stream

Check for failure of avformat_new_stream() and propagate
the error code.

Signed-off-by: Michael Niedermayer <michael@niedermayer.cc>

CVE: CVE-2022-3341

Upstream-Status: Backport [https://github.com/FFmpeg/FFmpeg/commit/
↪9cf652cef49d74afe3d454f27d49eb1a1394951e]

Comments: Refreshed Hunk
Signed-off-by: Narpat Mali <narpat.mali@windriver.com>
Signed-off-by: Bhabu Bindu <bhabu.bindu@kpit.com>
---
 libavformat/nutdec.c | 16 ++++++++-----
 1 file changed, 12 insertions(+), 4 deletions(-)
```

Una buona pratica consiste nell'includere l'identificativo CVE nel nome del file patch, nel messaggio di commit del file patch e, facoltativamente, nel messaggio di commit della ricetta.

`sbom-cve-check` acquisirà quindi queste informazioni e modificherà lo stato del CVE in `Patched` nei report generati.

Se l'analisi mostra che il problema CVE non ha un impatto sulla ricetta a causa della configurazione, della piattaforma, della versione o di altri motivi, il CVE può essere contrassegnato come `Ignored` utilizzando il flag della variabile `CVE_STATUS` con il motivo appropriato, che viene mappato a `Ignored`. La voce dovrebbe avere il seguente formato:

```
CVE_STATUS[CVE-2016-10642] = "cpe-incorrect: This is specific to the npm package
↪that installs cmake, so isn't relevant to OpenEmbedded"
```

Come accennato in precedenza, se i dati nel database CVE sono errati, si consiglia di correggere tali problemi direttamente nel database CVE (NVD nel caso di *OpenEmbedded-Core (OE-Core)*).

Si noti che se sono presenti più CVE con lo stesso stato e motivo, questi possono essere condivisi utilizzando la variabile `CVE_STATUS_GROUPS`.

Quando si analizzano le CVE, si raccomanda di:

- studiare le informazioni più recenti nel [database CVE](#).
- verificare come gli sviluppatori del componente software hanno affrontato il problema, ad esempio quale patch è stata applicata e quale release contiene la correzione.
- controllare cosa hanno fatto altre distribuzioni Linux, come [Debian](#), per analizzare e risolvere il problema.
- seguire gli avvisi di sicurezza di altre distribuzioni Linux.
- seguire le [mailing list pubbliche sulla sicurezza open source](#) per discussioni e notifiche anticipate sui bug CVE e sulle release software con le relative correzioni.

### 10.4.5 Dettagli di implementazione

Poiché *sbom-cve-check* è un tool esterno, la sua implementazione è descritta in dettaglio nella documentazione ufficiale: <https://sbom-cve-check.readthedocs.io/en/latest/index.html>

### 10.4.6 Vulnerabilità del kernel Linux

Dal momento che il kernel Linux è diventato un CVE Numbering Authority (CNA), il numero di CVE associato è aumentato drammaticamente. I team di sicurezza devono affrontare questi CVE per soddisfare i requisiti normativi e dei clienti. L'automazione sull'identificazione dei problemi aiuta a ridurre il carico di lavoro.

*OpenEmbedded-Core (OE-Core)* dispone di due script che aiutano a caratterizzare e filtrare le CVE che interessano il kernel Linux:

- `openembedded-core/meta/recipes-kernel/linux/generate-cve-exclusions.py`
- `openembedded-core/scripts/contrib/improve_kernel_cve_report.py`

#### `generate-cve-exclusions.py`

Quando si aggiorna una ricetta del kernel, è necessario eseguire manualmente uno script di supporto per aggiornare il *CVE\_STATUS* per la ricetta del kernel. Lo script può essere utilizzato per i kernel personalizzati.

Prima dobbiamo ottenere una versione aggiornata delle informazioni CVE dal *CVE Project*. Eseguirlo in questo modo:

```
$ git clone https://github.com/CVEProject/cvelistV5 ~/cvelistV5
```

Oppure, se è stato già clonato il repository, si devono scaricare i dati più recenti:

```
$ git -C ~/cvelistV5 pull
```

Successivamente, generare le informazioni *CVE\_STATUS* per la versione desiderata del kernel:

```
$ ./generate-cve-exclusions.py ~/cvelistV5 <version> > cve-exclusion_<kernel_
↪version>.inc
```

Esempio

```
$ git clone https://github.com/CVEProject/cvelistV5 ~/cvelistV5
$ cd openembedded-core/meta/recipes-kernel/linux/
```

(continues on next page)

(continua dalla pagina precedente)

```
$ ./generate-cve-exclusions.py ~/cvelistV5 6.12.27 > ~/meta-custom/recipes-kernel/
↳ linux/cve-exclusion_6.12.inc
```

Non dimenticare di aggiornare la ricetta del kernel con:

```
include cve-exclusion_6.12.inc
```

A questo punto, le informazioni CVE verranno aggiunte automaticamente al report `cve-check` o `vex`.

#### `improve_kernel_cve_report.py`

Lo script `openembedded-core/scripts/contrib/improve_kernel_cve_report.py` sfrutta i metadati CVE del kernel e la variabile `SPDX_INCLUDE_COMPILED_SOURCES` per aggiornare un file di report di output `.sbom-cve-check.yocto.json` (vedere la sezione *Verifica delle vulnerabilità in fase di build* per i dettagli su questi file di report). Riduce i falsi positivi CVE del 70%-80% e fornisce risposte dettagliate per tutte le CVE relative al kernel analizzando i file utilizzati per la compilazione del kernel. Lo script è indipendente dal processo di compilazione e può essere eseguito al di fuori dell'ambiente *BitBake*.

Lo script utilizza l'output di `vex` come input, insieme alle informazioni CVE del kernel Linux CNA, per arricchire il file di report con informazioni CVE aggiornate.

Il nome del file può essere specificato come argomento. Facoltativamente, può anche utilizzare l'elenco dei file compilati dal kernel `SPDX` per ignorare le CVE non interessate perché i file non sono stati compilati.

A tal fine, BitBake utilizza le informazioni di debug per estrarre i sorgenti utilizzati per la creazione di un binario. Pertanto, è necessario configurarlo nel kernel per estrarre i file compilati dal kernel.

Se si utilizza la ricetta `linux-yocto`, abilitarla aggiungendo quanto segue in un *configuration file* o in un file `.bbappend`:

```
KERNEL_EXTRA_FEATURES:append = " features/debug/debug-kernel.scc"
```

Oppure modificando la configurazione del kernel per includere le informazioni di debug di *DWARF4*.

Per ulteriori informazioni, consultare la sezione *Changing the Configuration* del Manuale di Sviluppo del Kernel Linux di Yocto Project.

Nell'esempio seguente, considereremo come ricetta del kernel utilizzata `linux-yocto`. Le istruzioni si applicano anche ad altre ricette del kernel con nomi diversi.

I sorgenti del kernel sono memorizzati in `tmp/pkgdata/<MACHINE>/debugsources/linux-yocto-debugsources.json.zstd`. Per includere le informazioni nel file `SPDX` e filtrare i file sorgente non utilizzati per la compilazione del kernel, aggiungere quanto segue in un *configuration file*:

```
SPDX_INCLUDE_COMPILED_SOURCES:pn-linux-yocto = "1"
```

Infine, salvare il file `recipe-linux-yocto.spdx.json` o il file `linux-yocto-debugsources.json.zstd` al di fuori della *build directory*.

Il file `SPDX` si trova in `tmp/deploy/spdx/<spdx_version>/<MACHINE>/recipes/recipe-linux-yocto.spdx.json`

Una volta ottenuti i dati di input, è necessario clonare o scaricare le informazioni CVE più recenti da <https://git.kernel.org>:

```
$ git clone https://git.kernel.org/pub/scm/linux/security/vulns.git ~/vulns
```

Oppure, se già presenti per un checkout:

```
$ git -C ~/vulns pull
```

Infine, eseguire lo script utilizzando uno degli esempi seguenti. I primi due esempi sono i più precisi e utilizzano il vecchio file `cve-summary.json`.

- Esempio con `--old-cve-report` come input:

```
$ python3 openembedded-core/scripts/contrib/improve_kernel_cve_report.py \
    --spdx tmp/deploy/spdx/3.0.1/qemux86_64/recipes/recipe-linux-yocto.spdx.
↪ json \
    --datadir ~/vulns \
    --old-cve-report build/tmp/deploy/images/<machine>/<image-name>-<machine>.
↪ rootfs.sbom-cve-check.yocto.json
```

- Esempio con il file `--debug-sources` al posto del file del kernel SPDX:

```
$ python3 openembedded-core/scripts/contrib/improve_kernel_cve_report.py \
    --debug-sources tmp/pkgdata/qemux86_64/debugsources/linux-yocto-
↪ debugsources.json.zstd \
    --datadir ~/vulns \
    --old-cve-report build/tmp/deploy/images/<machine>/<image-name>-<machine>.
↪ rootfs.sbom-cve-check.yocto.json
```

- Esempio con `--kernel-version`:

```
$ python3 openembedded-core/scripts/contrib/improve_kernel_cve_report.py \
    --spdx tmp/deploy/spdx/3.0.1/qemux86_64/recipes/recipe-linux-yocto.spdx.
↪ json \
    --kernel-version 6.12.27 \
    --datadir ~/vulns
```

Esempio di output per una CVE il cui stato è stato modificato in "Ignored" perché i file sorgente associati alla CVE non sono stati compilati: perché i file sorgente associati alla CVE non sono stati compilati:

```
{
  "id": "CVE-2025-38384",
  "status": "Ignored",
  "detail": "not-applicable-config",
  "summary": "In the Linux kernel, the following vulnerability has been resolved_
↪ (...)",
```

(continues on next page)

(continua dalla pagina precedente)

```

    "description": "Source code not compiled by config. {'drivers/mtd/nand/spi/core.  

    ↪c'}"
  }

```

Esempio di output per una CVE non inclusa nell'intervallo:

```

{
  "id": "CVE-2025-40017",
  "status": "Patched",
  "detail": "fixed-version",
  "summary": "In the Linux kernel, the following vulnerability has been resolved.  

  ↪ (...) ",
  "description": "only affects 6.15 onwards"
}

```

Esempio di output per una CVE vulnerabile:

```

{
  "id": "CVE-2024-58093",
  "status": "Unpatched",
  "detail": "version-in-range",
  "summary": "In the Linux kernel, the following vulnerability has been resolved.  

  ↪ (...) ",
  "description": "Needs backporting (fixed from 6.15)"
}

```

Esempio di output per una CVE rifiutata da Linux CNA:

```

{
  "id": "CVE-2025-38380",
  "status": "Ignored",
  "detail": "rejected",
  "summary": "In the Linux kernel, the following vulnerability has been resolved.  

  ↪ (...) ",
  "description": "Rejected by CNA"
}

```

## 10.5 Creazione di un Filesystem Root di Sola Lettura

Supponiamo che, per motivi di sicurezza, sia necessario disabilitare i permessi di scrittura del filesystem root del dispositivo di target (ovvero, sia necessario un filesystem root di sola lettura). Oppure, si potrebbe eseguire il sistema operativo del dispositivo da un'unità di archiviazione di sola lettura. In entrambi i casi, è possibile personalizzare l'immagine per ottenere tale comportamento.



**i Nota**

Il supporto di un filesystem root di sola lettura richiede che il sistema e le applicazioni non tentino di scrivere sul filesystem root. È necessario configurare tutte le parti del sistema di target in modo che scrivano altrove o che interrompano l'operazione in modo controllato qualora tentassero di scrivere sul filesystem root.

### 10.5.1 Creazione del Filesystem Root

Per creare il filesystem root di sola lettura, è sufficiente aggiungere la funzionalità "read-only-rootfs" all'immagine, solitamente in uno dei due modi seguenti. Il primo metodo consiste nell'aggiungere la funzionalità "read-only-rootfs" al file di configurazione dell'immagine tramite la variabile `IMAGE_FEATURES`:

```
IMAGE_FEATURES += "read-only-rootfs"
```

In alternativa, è possibile aggiungere la stessa funzionalità dal *configuration file* della propria distribuzione utilizzando la variabile `EXTRA_IMAGE_FEATURES` associata, come segue:

```
EXTRA_IMAGE_FEATURES = "read-only-rootfs"
```

Per ulteriori informazioni sull'utilizzo di queste variabili, consultare la sezione "*Customizing Images Using Custom IMAGE\_FEATURES and EXTRA\_IMAGE\_FEATURES*". Per informazioni sulle variabili, consultare i documenti `IMAGE_FEATURES` e `EXTRA_IMAGE_FEATURES`.

### 10.5.2 Script di Post-Installazione e Filesystem Root di Sola Lettura

È fondamentale assicurarsi che tutti gli script di post-installazione (`pkg_postinst`) per i pacchetti installati nell'immagine possano essere eseguiti al momento della creazione del filesystem root durante la compilazione sul sistema host. Questi script non possono essere eseguiti al primo avvio del dispositivo target. Con la funzionalità "read-only-rootfs" abilitata, il sistema di build si assicura che tutti gli script di post-installazione vengano eseguiti correttamente al momento della creazione del filesystem. Se uno qualsiasi di questi script deve ancora essere eseguito dopo la creazione del filesystem root, la compilazione fallisce immediatamente. Questi controlli in fase di build garantiscono che sia la compilazione a fallire, anziché il dispositivo target a fallire in un secondo momento durante il suo boot iniziale.

La maggior parte degli script di post-installazione comuni generati dal sistema di build per Yocto Project di default sono progettati per essere eseguiti durante la creazione del filesystem root (ad esempio, gli script di post-installazione per la cache dei font). Tuttavia, se si creano e si aggiungono script personalizzati, è necessario assicurarsi che possano essere eseguiti durante la creazione del filesystem.

Ecco alcuni problemi comuni che impediscono l'esecuzione degli script di post-installazione durante la creazione del filesystem root:

- *Mancato utilizzo di \$D davanti ai path assoluti:* Il sistema di build definisce `$D` quando viene creato il filesystem root. Inoltre, `$D` è vuoto quando lo script viene eseguito sul dispositivo target. Ciò implica due scopi per `$D`: garantire che i path siano validi sia nell'ambiente host che in quello target e verificare quale ambiente viene utilizzato per intraprendere le azioni appropriate.
- *Tentativo di eseguire processi specifici o dipendenti dall'architettura target:* È possibile ovviare a questi tentativi utilizzando strumenti nativi, che vengono eseguiti sul sistema host, per svolgere le stesse attività [task], oppure

eseguendo i processi in QEMU, che dispone della funzione `qemu_run_binary`. Per ulteriori informazioni, consultare la classe *qemu*.

### 10.5.3 Aree con Accesso in Scrittura

Con la funzionalità "read-only-rootfs" abilitata, qualsiasi tentativo da parte del sistema target di scrivere sul filesystem di root in fase di esecuzione fallisce. Di conseguenza, è necessario assicurarsi che i processi e le applicazioni che tentano questo tipo di scritture lo facciano su directory con accesso in scrittura (ad esempio `/tmp` o `/var/run`).

## 10.6 Firma dello Stato Condiviso

Il sistema di build *OpenEmbedded Build System* dispone di un meccanismo integrato che consente di risparmiare tempo di esecuzione riutilizzando artefatti precompilati: la *cache dello shared state* (*sstate cache*). Questi artefatti sono memorizzati in una directory (*SSTATE\_DIR*) e non sono firmati per default.

Questo documento illustra i passaggi per abilitare la firma dello shared state. Questa funzionalità dipende completamente da GPG, il che significa che gli esempi mostrati in questo documento utilizzeranno il tool da riga di comando `gpg`.

### 10.6.1 Requisiti dell'Host

Poiché GPG non fa parte dei requisiti *requisiti host* di default, sarà necessario installarlo sull'host.

Ad esempio, le distribuzioni basate su Debian lo forniscono tramite il pacchetto `gpg`. Installarlo come segue:

```
$ sudo apt-get install gpg
```

Verificare che l'installazione sia andata a buon fine controllando la versione di GPG:

```
$ gpg --version
```

### 10.6.2 Generazione di Una Coppia di Chiavi Pubblica e Privata con GPG

#### Nota

Questo passaggio è facoltativo se si dispone già di una coppia di chiavi pubblica e privata.

C'è bisogno di una coppia di chiavi pubblica e privata per due attività [task] indipendenti:

- Firmare gli artefatti di shared state che *OpenEmbedded Build System* genera con la propria **chiave privata**.
- Verificare gli artefatti di stato condivisi con la propria **chiave pubblica** quando si riutilizzano.

**i Nota**

Per ulteriori informazioni sulla crittografia a chiave pubblica, consultare la pagina di Wikipedia [https://en.wikipedia.org/wiki/Public-key\\_cryptography](https://en.wikipedia.org/wiki/Public-key_cryptography).

Col tool da riga di comando `gpg`, genera una nuova coppia di chiavi pubblica e privata:

```
$ gpg --full-generate-key
```

Guiderà attraverso i passaggi per la creazione della coppia di chiavi.

Una volta completata la procedura, si dovrebbe essere in grado di visualizzare la nuova chiave con il seguente comando:

```
$ gpg --list-keys
pub  ed25519 2026-04-17 [SC]
    4049A47E3AAA99D0250966DC5B97632FA7F4E942
uid          [ultimate] Antonin Godard (SState Signing) <antonin.godard\@bootlin.
    ↪com>
sub  cv25519 2026-04-17 [E]
```

Nell'esempio precedente, prendere nota dell'identificativo della chiave `4049A47E3AAA99D0250966DC5B97632FA7F4E942`. Questo verrà utilizzato per configurare la build.

### 10.6.3 Configurazione del Sistema di Build per la Firma degli Artefatti di Shared State

#### Posizione dello Shared State

Il sistema di build deve essere configurato per firmare i nuovi artefatti di shared state quando vengono generati. La generazione di nuovi artefatti avviene al termine dell'esecuzione di un task.

Per le sezioni seguenti, supponiamo che il sistema di build abbia la directory di shared state (*SSTATE\_DIR*) definita come segue:

```
SSTATE_DIR = "${TOPDIR}/sstate-cache"
```

Supponendo che questa directory e la directory temporanea (*TMPDIR*) siano vuote, eseguiamo il task `create_recipe_spdx` della ricetta `gettext-minimal-native`:

```
$ bitbake gettext-minimal-native -c create_recipe_spdx
```

Utilizzeremo questo comando come esempio in tutto il documento.

Dopo l'esecuzione, la directory di shared state dovrebbe essere popolata con nuovi file:

```
$ find $BUILDDIR/sstate-cache/ -name "*gettext-minimal-native*create_recipe_spdx*"
sstate-cache/universal/a3/6e/sstate:gettext-minimal-native:x86_64-linux:1.0:r0:x86_
```

(continues on next page)

(continua dalla pagina precedente)

```

↪64:14:a36ef66df6b8c0cb5a849bc70a99dcfd61e4bacd11cefe6bbaf4978b2b3b617a_create_
↪recipe_spdx.tar.zst
sstate-cache/universal/a3/6e/sstate:gettext-minimal-native:x86_64-linux:1.0:r0:x86_
↪64:14:a36ef66df6b8c0cb5a849bc70a99dcfd61e4bacd11cefe6bbaf4978b2b3b617a_create_
↪recipe_spdx.tar.zst.siginfo

```

Questi sono gli artefatti di shared state predefiniti generati da *OpenEmbedded Build System*. Non sono firmati con GPG per default, quindi vediamo come aggiungere la firma a questi artefatti.

### Nota

Nonostante il nome, il file *siginfo* non è correlato alla firma GPG.

## Abilitazione della Firma dello Shared State

Creare un nuovo *configuration file* sul proprio host **in una posizione sicura** e aggiungere le due seguenti istruzioni:

```

SSTATE_VERIFY_SIG = "1"
SSTATE_SIG_KEY = "4049A47E3AAA99D0250966DC5B97632FA7F4E942"
SSTATE_SIG_PASSPHRASE = "<your GPG key passphrase>"

```

Si consiglia di inserire queste istruzioni in un file separato, poiché contengono informazioni riservate e non devono essere condivise. Per questo esempio, supponiamo che il file si chiami `conf/sstate-sig-key.conf`.

Ci si può assicurare che questo file sia di proprietà e non leggibile da altri utenti con:

```

$ chown $USER:$USER conf/sstate-sig-key.conf
$ chmod o-rwx conf/sstate-sig-key.conf

```

Le istruzioni in questo file definiscono:

- *SSTATE\_VERIFY\_SIG*: impostando questa variabile su "1" si abilita la funzionalità di firma dello shared state.
- *SSTATE\_SIG\_KEY*: l'identificativo della chiave GPG per la firma degli artefatti dello shared state con la chiave privata.

Nell'esempio, questo corrisponde all'identificativo visualizzato con il comando `gpg --list-keys precedente`.

- *SSTATE\_SIG\_PASSPHRASE*: la passphrase utilizzata per proteggere la chiave privata, scelta al momento della creazione della coppia di chiavi.

Testiamo la configurazione:

1. Continuando con l'esempio `gettext-minimal-native`, rimuoviamo innanzitutto gli artefatti di stato condiviso esistenti, per assicurarci che gli artefatti di shared state per il proprio task `do_create_recipe_spdx` vengano rigenerati:

```

$ rm -r sstate-cache/

```

2. Eseguiamo il task `create_recipe_spdx` per `gettext-minimal-native`, ma questa volta passiamo il nuovo file `sstate-sig-key.conf` a *BitBake*:

```
$ bitbake -R conf/sstate-sig-key.conf gettext-minimal-native -c create_recipe_
↳ spdx
```

Elenchiamo nuovamente i file nella directory dello shared state:

```
$ find sstate-cache/ -name "*gettext-minimal-native*create_recipe_spdx*"
sstate-cache/universal/a3/6e/sstate:gettext-minimal-native:x86_64-linux:1.0:r0:x86_
↳ 64:14:a36ef66df6b8c0cb5a849bc70a99dcfd61e4bacd11cefe6bbaf4978b2b3b617a_create_
↳ recipe_spdx.tar.zst
sstate-cache/universal/a3/6e/sstate:gettext-minimal-native:x86_64-linux:1.0:r0:x86_
↳ 64:14:a36ef66df6b8c0cb5a849bc70a99dcfd61e4bacd11cefe6bbaf4978b2b3b617a_create_
↳ recipe_spdx.tar.zst.sig
sstate-cache/universal/a3/6e/sstate:gettext-minimal-native:x86_64-linux:1.0:r0:x86_
↳ 64:14:a36ef66df6b8c0cb5a849bc70a99dcfd61e4bacd11cefe6bbaf4978b2b3b617a_create_
↳ recipe_spdx.tar.zst.siginfo
```

È stato creato un nuovo file `.sig`: questo significa che l'artefatto è stato firmato correttamente e la firma è memorizzata in un file `.sig` separato.

### 10.6.4 Verifica degli Artefatti Firmati dello Shared State

Ora che è stato configurata la build per firmare gli artefatti dello shared state, vediamo come so possono verificare con la corrispondente chiave pubblica della chiave privata.

#### Nota

La firma dello shared state e la sua verifica possono avvenire su due host diversi, il che significa che un host può occuparsi della firma mentre un altro si limita a verificare gli artefatti. Questa soluzione è preferibile in quanto la chiave privata non dovrebbe essere condivisa tra più host.

Da un *configuration file*, come ad esempio il *file di configurazione del sito*, includere le seguenti istruzioni:

```
SSTATE_VERIFY_SIG = "1"
SSTATE_VALID_SIGS = "5B97632FA7F4E942"
```

Queste dichiarazioni definiscono:

- `SSTATE_VERIFY_SIG`: impostando questa variabile su "1" si abilita la funzionalità di firma dello shared state.
- `SSTATE_VALID_SIGS`: un elenco di identificatori di chiave separati da spazi per i quali sono accettati artefatti di shared state.

Ciò significa che lo stato condiviso verrà riutilizzato **solo se è stato firmato con la chiave privata corrispondente all'identificatore di chiave**.

Si noterà qui la forma abbreviata dell'identificativo della chiave, ovvero gli ultimi 16 caratteri dell'identificativo della chiave in forma estesa mostrato con `gpg --list-keys` (in grassetto qui sotto):

```
pub    ed25519 2026-04-17 [SC]
        4049A47E3AAA99D0250966DC5B97632FA7F4E942
uid          [ultimate] Antonin Godard (SState Signing) <antonin.
        ↪godard@bootlin.com>
sub    cv25519 2026-04-17 [E]
```

Confermiamo che la verifica della firma funzioni:

1. Innanzitutto, rimuoviamo gli output temporanei (*TMPDIR*) dalle build precedenti, in modo che *OpenEmbedded Build System* ricompili tutto utilizzando lo shared state:

```
$ rm -rf tmp/
```

2. Quindi, eseguiamo nuovamente il task:

```
$ bitbake gettext-minimal-native -c create_recipe_spdx
```

3. Per assicurarci che l'artefatto dello shared state sia stato utilizzato correttamente, cerchiamo il task *setscene* per *create\_recipe\_spdx* nell'ultimo file di log di *BitBake*:

```
$ grep create_recipe_spdx_setscene tmp/log/cooker/<machine>/console-latest.log
NOTE: Running setscene task 1 of 1 (../layers/openembedded-core/meta/recipes-
        ↪core/gettext/gettext-minimal-native_1.0.bb:do_create_recipe_spdx_setscene)
NOTE: recipe gettext-minimal-native-1.0-r0: task do_create_recipe_spdx_
        ↪setscene: Started
NOTE: recipe gettext-minimal-native-1.0-r0: task do_create_recipe_spdx_
        ↪setscene: Succeeded
```

Lo shared state è stato verificato e utilizzato correttamente!

### Nota

Per verificare che la verifica dello shared state funzioni correttamente, è possibile impostare un identificatore di chiave pubblica "fake" in *SSTATE\_VALID\_SIGS*:

```
SSTATE_VALID_SIGS = "CAFECAFECAFECAFE"
```

Rimuovere nuovamente gli output temporanei:

```
$ rm -r tmp/
```

Ora, provare a eseguire il task:

```
$ bitbake gettext-minimal-native -c create_recipe_spdx
```

Dovrebbero essere visualizzati dei warning da *BitBake* sulla console:

```
WARNING: gettext-minimal-native-1.0-r0 do_create_recipe_spdx_setscene: No_
        ↪accepted signatures found. Good signatures found: 5B97632FA7F4E942.
WARNING: gettext-minimal-native-1.0-r0 do_create_recipe_spdx_setscene: Cannot_
```

```
→verify signature on sstate package ../build/sstate-cache/universal/a3/6e/
→sstate:gettext-minimal-native:x86_64-linux:1.0:r0:x86_
→64:14:a36ef66df6b8c0cb5a849bc70a99dcfd61e4bacd11cefe6bbaf4978b2b3b617a_create_
→recipe_spdx.tar.zst, skipping acceleration...
WARNING: gettext-minimal-native-1.0-r0 do_create_recipe_spdx_setscene: No sstate_
→archive obtainable, will run full task instead.
WARNING: Logfile for failed setscene task is ../build/tmp/work/x86_64-linux/
→gettext-minimal-native/1.0/temp/log.do_create_recipe_spdx_setscene.6994
WARNING: Setscene task (../layers/openembedded-core/meta/recipes-core/gettext/
→gettext-minimal-native_1.0.bb:do_create_recipe_spdx_setscene) failed with exit_
→code '1' - real task will be run instead
```

Come si può notare, questo non impedisce a *BitBake* di proseguire, ma viene eseguito il task reale invece di riutilizzare lo shared state.

---

The Yocto Project ®

<docs@lists.yoctoproject.org>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.





---

## Manuale di Profilazione e Tracing di Yocto Project

---

### 11.1 Manuale di Profilazione e Tracing di Yocto Project

#### 11.1.1 Introduzione

Yocto Project include una serie di strumenti di tracing [tracciamento] e profilazione: questo manuale ne descrive l'utilizzo di base e mostra, tramite esempi, come impiegarli per analizzare il comportamento di applicazioni e sistemi.

I tool presentati sono, per la maggior parte, completamente aperti e dispongono di una documentazione completa e/o esaustiva che può essere utilizzata per risolvere praticamente qualsiasi problema si possa incontrare in Linux. Ogni sezione che descrive un tool specifico contiene link alla relativa documentazione e al sito web.

Lo scopo di questo manuale è presentare una serie di idiomi di tracing e profilazione comuni e generalmente utili, insieme alla loro applicazione (ove appropriato) a ciascun tool, nel contesto di una metodologia di analisi approfondita di carattere generale, applicabile alla risoluzione di un'ampia gamma di problemi. Per assistenza su utilizzi e problematiche più avanzate, fare riferimento alla documentazione e/o ai siti web forniti per ciascun tool.

La sezione finale di questo manuale è una raccolta di esempi pratici che aggiorneremo costantemente man mano che risolveremo nuovi problemi utilizzando i tool: non esitate a suggerire ulteriori esempi.

#### 11.1.2 Configurazione Generale

La maggior parte degli strumenti è disponibile solo nelle immagini `sdk` o nelle immagini create dopo aver aggiunto `tools-profile` alla variabile `EXTRA_IMAGE_FEATURES`.

Pertanto, per poter accedere a tutti gli strumenti descritti qui, è possibile creare e avviare un'immagine `sdk`, ad esempio una delle seguenti:

```
$ bitbake core-image-sato-sdk
$ bitbake core-image-weston-sdk
$ bitbake core-image-rt-sdk
```

In alternativa, è possibile aggiungere `tools-profile` alla riga `EXTRA_IMAGE_FEATURES` nel file `build/conf/local.conf`:

```
EXTRA_IMAGE_FEATURES:append = " tools-profile"
```

Se si utilizza il metodo `tools-profile`, non è necessario creare un'immagine sdk: gli strumenti di tracing e profilazione saranno inclusi anche nelle immagini non sdk, ad esempio:

```
$ bitbake core-image-sato
```

### **i** Nota

Per default, il sistema di compilazione Yocto rimuove i simboli dai binari che impacchetta, il che rende difficile l'utilizzo di alcuni tool.

È possibile evitarlo impostando la variabile `INHIBIT_PACKAGE_STRIP` su "1" nel file `build/conf/local.conf` durante la creazione dell'immagine:

```
INHIBIT_PACKAGE_STRIP = "1"
```

L'impostazione sopra descritta aumenterà notevolmente le dimensioni dell'immagine.

Se è stata già creata un'immagine senza pacchetti, si possono generare pacchetti di debug (`xxx-dbg`) che si potranno installare manualmente secondo necessità.

Per generare informazioni di debug per i pacchetti, è possibile aggiungere `dbg-pkgs` a `EXTRA_IMAGE_FEATURES` nel file `build/conf/local.conf`. Ad esempio:

```
EXTRA_IMAGE_FEATURES:append = " dbg-pkgs"
```

Inoltre, per generare il tipo corretto di informazioni di debug, è necessario impostare anche `PACKAGE_DEBUG_SPLIT_STYLE` nel file `build/conf/local.conf`:

```
PACKAGE_DEBUG_SPLIT_STYLE = 'debug-file-directory'
```

## 11.2 Architettura Generale dei Tool di Tracing e Profilazione di Linux

### 11.2.1 Architettura dei Tool di Tracing e Profilazione

Potrebbe sembrare sorprendente trovare una sezione dedicata alla 'architettura generale' di quello che apparentemente è un insieme casuale di tool di tracing che costituiscono lo spazio di tracing e profilazione di Linux. In realtà,

però, negli ultimi anni questo insieme di tool apparentemente eterogeneo ha iniziato a convergere verso un insieme "centrale" di meccanismi sottostanti:

- static tracepoints
- dynamic tracepoints
  - kprobes
  - uprobes
- il perf\_events subsystem
- debugfs

#### Unire il Tutto

Anziché elencare qui come ogni tool utilizza questi meccanismi comuni, riquadri di testo come questo indicheranno gli usi specifici in ogni strumento man mano che vengono menzionati nel corso del testo.

## 11.3 Utilizzo di Base (con esempi) per ciascuno dei Tool di Tracing di Yocto

Questo capitolo presenta esempi di utilizzo di base per ciascuno dei tool di tracing.

### 11.3.1 perf

Lo tool perf è lo strumento di profilazione e tracing [tracciamento] incluso nel kernel Linux.

Non lasciatevi ingannare dal fatto che faccia parte del kernel: non serve solo per tracciare e profilare il kernel stesso. È possibile utilizzarlo per tracciare e profilare il solo kernel, ma anche per profilare applicazioni specifiche separatamente (con o senza contesto kernel), e persino per tracciare e profilare simultaneamente il kernel e tutte le applicazioni presenti sul sistema, ottenendo così una visione completa di ciò che sta accadendo.

Per molti aspetti, perf si propone di essere un superset di tutti i tool di tracciamento e profilazione attualmente disponibili in Linux, inclusi tutti gli altri strumenti descritti in questa guida. Negli ultimi due anni, perf ha integrato gran parte delle funzionalità di questi altri strumenti e, allo stesso tempo, questi ultimi hanno rimosso ampie porzioni delle loro funzionalità precedenti, sostituendole con chiamate alle funzionalità equivalenti ora implementate dal sottosistema perf. È probabile che a un certo punto questi altri strumenti diventeranno completamente obsoleti e scompariranno. Fino ad allora, tratteremo questi altri strumenti in queste pagine e, in molti casi, mostreremo come ottenere gli stessi risultati con perf e gli altri tool quando ciò si rivela utile.

La descrizione seguente illustra alcuni dei metodi più comuni con cui probabilmente si vorrà utilizzare il tool; la documentazione completa è disponibile all'interno del tool stesso o nelle pagine del manuale *perf(1)*.

## Configurazione di perf

Per questa sezione, daremo per scontato che sia stata già eseguito la configurazione di base descritta nella sezione "*Configurazione Generale*".

In particolare, si otterrà il massimo da perf se si profila un'immagine creata con quanto segue in un *configuration file*:

```
INHIBIT_PACKAGE_STRIP = "1"
```

perf viene eseguito principalmente sul sistema target. È possibile archiviare i dati di profilazione e copiarli sull'host per l'analisi, ma per il resto di questo documento si presuppone che si sia connessi all'host tramite SSH ed si eseguiranno i comandi perf sul sistema target.

## Utilizzo di Base di perf

Il tool perf è praticamente autoesplicativo. Per ricordare i comandi disponibili, basta digitare `perf`, che mostrerà l'utilizzo di base insieme ai sottocomandi disponibili:

```
root@crownbay:~# perf

usage: perf [--version] [--help] COMMAND [ARGS]

The most commonly used perf commands are:

  annotate      Read perf.data (created by perf record) and display annotated
↳code
  archive       Create archive with object files with build-ids found in perf.
↳data file
  bench         General framework for benchmark suites
  buildid-cache Manage build-id cache.
  buildid-list  List the buildids in a perf.data file
  diff          Read two perf.data files and display the differential profile
  evlist        List the event names in a perf.data file
  inject        Filter to augment the events stream with additional information
  kmem          Tool to trace/measure kernel memory(slab) properties
  kvm           Tool to trace/measure kvm guest os
  list          List all symbolic event types
  lock          Analyze lock events
  probe         Define new dynamic tracepoints
  record        Run a command and record its profile into perf.data
  report        Read perf.data (created by perf record) and display the profile
  sched         Tool to trace/measure scheduler properties (latencies)
  script        Read perf.data (created by perf record) and display trace output
  stat          Run a command and gather performance counter statistics
  test          Runs sanity tests.
  timechart     Tool to visualize total system behavior during a workload
  top           System profiling tool.
```

(continues on next page)

(continua dalla pagina precedente)

See `'perf help COMMAND'` for more information on a specific command.

## Utilizzo di perf per la Profilazione di Base

Come semplice caso di test, profiliamo il comando `wget` di un file piuttosto grande, un caso minimamente interessante perché include aspetti di I/O sia di file che di rete e, almeno nel caso delle immagini Yocto standard, è implementato come parte di BusyBox, quindi i metodi che utilizziamo per analizzarlo possono essere usati in modo simile a tutta la gamma di applet BusyBox supportate in Yocto:

```
root@crownbay:~# rm linux-2.6.19.2.tar.bz2; \
    wget https://downloads.yoctoproject.org/mirror/sources/linux-2.6.
↳19.2.tar.bz2
```

Il modo più rapido e semplice per ottenere dati generali di base su cosa sta succedendo per un particolare carico di lavoro è profilarlo usando `perf stat`. Questo comando esegue un'analisi delle prestazioni utilizzando alcuni contatori predefiniti e visualizza la somma dei valori al termine dell'esecuzione:

```
root@crownbay:~# perf stat wget https://downloads.yoctoproject.org/mirror/sources/
↳linux-2.6.19.2.tar.bz2
Connecting to downloads.yoctoproject.org (140.211.169.59:80)
linux-2.6.19.2.tar.b 100% |*****|
↳41727k 0:00:00 ETA

Performance counter stats for 'wget https://downloads.yoctoproject.org/mirror/
↳sources/linux-2.6.19.2.tar.bz2':

    4597.223902 task-clock                #    0.077 CPUs utilized
      23568 context-switches             #    0.005 M/sec
         68 CPU-migrations               #    0.015 K/sec
        241 page-faults                 #    0.052 K/sec
   3045817293 cycles                     #    0.663 GHz
<not supported> stalled-cycles-frontend
<not supported> stalled-cycles-backend
   858909167 instructions                #    0.28  insns per cycle
   165441165 branches                   #   35.987 M/sec
   19550329 branch-misses                #   11.82% of all branches

   59.836627620 seconds time elapsed
```

Un test così semplice non sempre fornisce risultati interessanti, ma a volte sì (bug report [Slow write speed on live images with denzil](#)).

Inoltre, si noti che `perf stat` non è limitato a un set fisso di contatori: praticamente qualsiasi evento elencato nell'output di `perf list` può essere conteggiato da `perf stat`. Ad esempio, supponiamo di voler visualizzare un

riepilogo di tutti gli eventi relativi all'allocazione/liberazione della memoria del kernel, insieme ai cache hit e ai cache miss:

```
root@crownbay:~# perf stat -e kmem:* -e cache-references -e cache-misses wget_
↳https://downloads.yoctoproject.org/mirror/sources/linux-2.6.19.2.tar.bz2
Connecting to downloads.yoctoproject.org (140.211.169.59:80)
linux-2.6.19.2.tar.b 100% |*****|
↳41727k 0:00:00 ETA

Performance counter stats for 'wget https://downloads.yoctoproject.org/mirror/
↳sources/linux-2.6.19.2.tar.bz2':

    5566 kmem:kmalloc
  125517 kmem:kmem_cache_alloc
         0 kmem:kmalloc_node
         0 kmem:kmem_cache_alloc_node
   34401 kmem:kfree
   69920 kmem:kmem_cache_free
    133 kmem:mm_page_free
     41 kmem:mm_page_free_batched
   11502 kmem:mm_page_alloc
   11375 kmem:mm_page_alloc_zone_locked
         0 kmem:mm_page_pcpu_drain
         0 kmem:mm_page_alloc_extfrag
  66848602 cache-references
  2917740 cache-misses          #    4.365 % of all cache refs

  44.831023415 seconds time elapsed
```

Come si può vedere, `perf stat` ci offre un modo semplice e veloce per ottenere una panoramica di ciò che potrebbe accadere in relazione a una serie di eventi, ma normalmente avremmo bisogno di maggiori dettagli per comprendere appieno la situazione e poter intervenire in modo efficace.

Per approfondire ulteriormente, possiamo utilizzare `perf record`/`perf report`, che raccolgono i dati di profilazione e li presentano tramite un'interfaccia utente interattiva basata su testo (oppure semplicemente come testo se specifichiamo `--stdio a perf report`).

Come primo tentativo di profilazione di questo carico di lavoro, eseguiremo semplicemente `perf record`, passandogli il carico di lavoro che vogliamo profilare (tutto ciò che segue `perf record` e le eventuali opzioni di `perf` che gli passiamo - in questo caso nessuna, verrà eseguito in una nuova shell). `perf` raccoglie campioni fino alla terminazione del processo e li registra in un file chiamato `perf.data` nella directory di lavoro corrente:

```
root@crownbay:~# perf record wget https://downloads.yoctoproject.org/mirror/
↳sources/linux-2.6.19.2.tar.bz2

Connecting to downloads.yoctoproject.org (140.211.169.59:80)
```

(continues on next page)

(continua dalla pagina precedente)

```
linux-2.6.19.2.tar.b 100% | ***** |
↪41727k 0:00:00 ETA
[ perf record: Woken up 1 times to write data ]
[ perf record: Captured and wrote 0.176 MB perf.data (~7700 samples) ]
```

Per visualizzare i risultati in un'interfaccia utente testuale (tui), è sufficiente eseguire `perf report`, che leggerà il file `perf.data` nella directory di lavoro corrente e visualizzerà i risultati in un'interfaccia utente interattiva:

```
root@crownbay:~# perf report
```

```

trz@empanada:~
File Edit View Search Terminal Help
Events: 4K cycles, Thread: wget(1231)
3.86% wget [kernel.kallsyms] [k] sub_preempt_count
3.47% wget [kernel.kallsyms] [k] add_preempt_count
3.16% wget [kernel.kallsyms] [k] read_hpet
1.95% wget [kernel.kallsyms] [k] __copy_to_user_ll
1.92% wget [kernel.kallsyms] [k] system_call
1.82% wget [kernel.kallsyms] [k] __copy_from_user_ll_nozero
1.76% wget [kernel.kallsyms] [k] get_parent_ip
1.67% wget [kernel.kallsyms] [k] ext3_mark_inode_dirty
1.67% wget busybox [.] 0x000651e3
1.54% wget [kernel.kallsyms] [k] __find_get_block
1.37% wget [kernel.kallsyms] [k] ext3_get_blocks_handle
1.22% wget [kernel.kallsyms] [k] do_sys_poll
1.16% wget [kernel.kallsyms] [k] journal_add_journal_head
1.10% wget [kernel.kallsyms] [k] __block_write_begin
1.07% wget [kernel.kallsyms] [k] tcp_recvmmsg
1.02% wget [kernel.kallsyms] [k] in_lock_functions
1.01% wget [kernel.kallsyms] [k] ext3_new_blocks
0.97% wget [kernel.kallsyms] [k] do_get_write_access
0.94% wget [kernel.kallsyms] [k] memset
0.88% wget [kernel.kallsyms] [k] fget_light
0.84% wget [kernel.kallsyms] [k] ioread32
0.82% wget [kernel.kallsyms] [k] __ext3_get_inode_loc
0.79% wget [kernel.kallsyms] [k] bit_waitqueue
0.78% wget [kernel.kallsyms] [k] __schedule
0.74% wget libc-2.16.so [.] read
0.73% wget [kernel.kallsyms] [k] journal_dirty_metadata
0.73% wget [kernel.kallsyms] [k] _raw_spin_lock
0.72% wget libc-2.16.so [.] 0x0006f4de
0.67% wget [kernel.kallsyms] [k] fsnotify
0.67% wget [kernel.kallsyms] [k] kmem_cache_alloc
0.67% wget [kernel.kallsyms] [k] debug_smp_processor_id
0.66% wget [kernel.kallsyms] [k] ext3_ordered_write_end
0.64% wget [kernel.kallsyms] [k] journal_dirty_data
0.62% wget [kernel.kallsyms] [k] find_busiest_group
0.62% wget [kernel.kallsyms] [k] __rcu_read_unlock
0.61% wget [kernel.kallsyms] [k] radix_tree_lookup_element
0.60% wget [kernel.kallsyms] [k] kmem_cache_free
0.59% wget [kernel.kallsyms] [k] kfree
0.58% wget [kernel.kallsyms] [k] __mark_inode_dirty
0.57% wget [kernel.kallsyms] [k] ext3_journal_start_sb
Press '?' for help on key bindings

```

Lo screenshot qui sopra mostra un profilo "piatto", con una voce per ogni "bucket" corrispondente alle funzioni profilate durante l'esecuzione del profilo, ordinate dalla più frequente alla meno frequente (perf offre opzioni per ordinare in vari modi e con diverse chiavi, nonché per visualizzare solo le voci al di sopra di una determinata soglia e così via - consultare la documentazione di perf per maggiori dettagli). Si noti che questo include sia le funzioni dello spazio utente (voci contenenti `[.]`) sia le funzioni del kernel attribuite al processo (voci contenenti `[k]`). perf dispone di modificatori da riga di comando che possono essere utilizzati per limitare la profilazione allo spazio kernel o allo spazio utente, tra le altre opzioni.

Si noti inoltre che il report sopra riportato mostra una voce per `busybox`, ovvero l'eseguibile che implementa `wget` in Yocto, ma che invece di un nome di funzione utile, in quella voce viene visualizzato un valore esadecimale poco leggibile. I passaggi seguenti mostreranno come risolvere questo problema.

Prima di procedere, però, proviamo a eseguire un profilo diverso, uno che mostri qualcosa di un po' più interessante. L'unica differenza tra il nuovo profilo e il precedente è l'aggiunta dell'opzione `-g`, che registrerà non solo l'indirizzo di una funzione campionata, ma anche l'intera catena di chiamate a quella funzione:

```
root@crownbay:~# perf record -g wget https://downloads.yoctoproject.org/mirror/
↳sources/linux-2.6.19.2.tar.bz2
Connecting to downloads.yoctoproject.org (140.211.169.59:80)
linux-2.6.19.2.tar.b 100% |*****|
↳41727k 0:00:00 ETA
[ perf record: Woken up 3 times to write data ]
[ perf record: Captured and wrote 0.652 MB perf.data (~28476 samples) ]

root@crownbay:~# perf report
```

```

File Edit View Search Terminal Help
Events: 4K cycles
+ 1.77% wget [kernel.kallsyms] [k] __copy_from_user_ll_nozero
- 1.77% wget [kernel.kallsyms] [k] __copy_to_user_ll
  - __copy_to_user_ll
    - 90.87% copy_to_user
      - 97.79% memcpy_toiovec
        - skb_copy_datagram_iovec
          - 89.99% tcp_recvmg
            inet_recvmg
            sock_aio_read
            do_sync_read
            vfs_read
            sys_read
            syscall_call
            read
          - 10.01% skb_copy_datagram_iovec
            tcp_recvmg
            inet_recvmg
            sock_aio_read
            do_sync_read
            vfs_read
            sys_read
            syscall_call
            read
        + 2.21% sys_clock_gettime
      - 6.75% sys_clock_gettime
        syscall_call
        syscall
        0x808c05
    - 2.38% memcpy_toiovec
      skb_copy_datagram_iovec
      tcp_recvmg
      inet_recvmg
      sock_aio_read
      do_sync_read
      vfs_read
      sys_read
      syscall_call
      read
+ 1.43% wget [kernel.kallsyms] [k] ext3_get_blocks_handle
+ 1.42% wget [kernel.kallsyms] [k] tcp_recvmg
Press '?' for help on key bindings

```

Utilizzando la visualizzazione del grafico delle chiamate, possiamo vedere non solo quali funzioni hanno impiegato più tempo, ma anche un riepilogo di come sono state chiamate e possiamo imparare qualcosa su come il programma interagisce con il kernel.

Notate che ogni voce nella schermata precedente ora contiene un `+` sul lato sinistro. Questo significa che possiamo espandere la voce e analizzare in dettaglio le catene di chiamate che alimentano quella voce. Premendo `Enter` su una qualsiasi di esse, si espanderà la catena di chiamate (è anche possibile premere `E` per espanderle tutte contemporaneamente o `C` per compprimerle tutte).



Nella schermata qui sopra, abbiamo attivato la voce `__copy_to_user_ll()` e diversi sotto-nodi fino in fondo. Questo ci permette di vedere quali catene di chiamate hanno contribuito alla funzione `__copy_to_user_ll()` profilata, che ha contribuito per l'1,77% al profilo totale.

Per spiegare brevemente queste catene di chiamate, pensiamo a cosa succede a un livello generale quando si esegue `wget` per scaricare un file dalla rete. In pratica, i dati arrivano al kernel tramite la connessione di rete (socket) e vengono passati al programma in spazio utente `wget` (che in realtà fa parte di BusyBox, ma questo non è importante per ora), il quale prende i buffer che il kernel gli passa e li scrive su un file su disco per salvarli.

La parte di questo processo che stiamo esaminando negli stack di chiamate sopra riportati è quella in cui il kernel passa i dati letti dal socket a `wget`, ovvero una `copy-to-user`.

Si noti inoltre che anche in questo caso il valore esadecimale viene visualizzato nello stack di chiamate, qui nella funzione `sys_clock_gettime()` espansa. Più avanti vedremo che si risolve in una chiamata di funzione in spazio utente in BusyBox.


```

Events: 4K cycles
+ 3.60% wget [kernel.kallsyms] [k] sub_preempt_count
+ 3.12% wget [kernel.kallsyms] [k] read_hpet
+ 2.73% wget [kernel.kallsyms] [k] add_preempt_count
+ 2.48% wget busybox [.] 0x000c0dd
+ 2.21% wget [kernel.kallsyms] [k] get_parent_ip
+ 1.94% wget [kernel.kallsyms] [k] system_call
+ 1.88% wget [kernel.kallsyms] [k] __find_get_block
+ 1.77% wget [kernel.kallsyms] [k] __copy_from_user_ll_nzero
- __copy_from_user_ll_nzero
- 91.57% iov_iter_copy_from_user_atomic
  generic_file_buffered_write
  __generic_file_aio_write
  generic_file_aio_write
  do_sync_write
  vfs_write
  sys_write
  syscall_call
  write
- 8.43% generic_file_buffered_write
  __generic_file_aio_write
  generic_file_aio_write
  do_sync_write
  vfs_write
  sys_write
  syscall_call
  write
+ 1.77% wget [kernel.kallsyms] [k] __copy_to_user_ll
+ 1.43% wget [kernel.kallsyms] [k] ext3_get_blocks_handle
+ 1.42% wget [kernel.kallsyms] [k] tcp_recvmmsg
+ 1.41% wget [kernel.kallsyms] [k] ext3_new_blocks
+ 1.34% wget [kernel.kallsyms] [k] __block_write_begin
+ 1.32% wget [kernel.kallsyms] [k] in_lock_functions
+ 1.32% wget [kernel.kallsyms] [k] ext3_mark_inode_dirty
+ 1.17% wget [kernel.kallsyms] [k] memset
+ 1.13% wget [kernel.kallsyms] [k] debug_smp_processor_id
+ 1.08% wget [kernel.kallsyms] [k] __schedule
+ 1.05% wget [kernel.kallsyms] [k] journal_add_journal_head
+ 0.92% wget [kernel.kallsyms] [k] __ext3_get_inode_loc
+ 0.83% wget [kernel.kallsyms] [k] do_sys_poll
+ 0.81% wget [kernel.kallsyms] [k] journal_dirty_metadata
Press '?' for help on key bindings

```

Lo screenshot sopra mostra l'altra metà del percorso dei dati: dai buffer in spazio utente del programma `wget` al disco. Per trasferire i buffer su disco, il programma `wget` esegue una `write(2)`, che effettua una `copy-from-user` al kernel, il quale poi si occupa, tramite un percorso indiretto (probabilmente presente anche da qualche parte nei dati di profilo), di trasferire i dati in modo sicuro su disco.

Ora che abbiamo visto la struttura di base dei dati del profilo e le nozioni fondamentali su come estrarne informazioni utili, torniamo al compito principale e cerchiamo di capire dove viene impiegato il tempo nel programma che stiamo profilando, `wget`. Ricordiamo che `wget` è implementato come applet in BusyBox, quindi, sebbene il nome del processo sia `wget`, l'eseguibile che ci interessa è `busybox`. Pertanto, espandiamo la prima voce contenente BusyBox:



Anche in questo caso, prima di espandere la voce, abbiamo notato che la funzione era etichettata con un valore esadecimale anziché con un simbolo, come avviene per la maggior parte delle voci del kernel. Espandere la voce BusyBox non migliora la situazione.

Il problema è che perf non riesce a trovare le informazioni sui simboli per il binario `busybox`, che vengono rimosse dal sistema di build Yocto.

Un modo per aggirare il problema è inserire quanto segue in un *configuration file* durante la creazione dell'immagine:

```
INHIBIT_PACKAGE_STRIP = "1"
```

Tuttavia, abbiamo già un'immagine con i binari rimossi, quindi cosa possiamo fare per far sì che perf risolva i simboli? Fondamentalmente, dobbiamo installare le informazioni di debug per il pacchetto BusyBox.

Per generare le informazioni di debug per i pacchetti nell'immagine, possiamo aggiungere `dbg-pkgs` a `EXTRA_IMAGE_FEATURES` in `build/conf/local.conf`. Ad esempio:

```
EXTRA_IMAGE_FEATURES:append = " dbg-pkgs"
```

Inoltre, per generare il tipo di informazioni di debug che perf comprende, dobbiamo anche impostare `PACKAGE_DEBUG_SPLIT_STYLE` in un *configuration file*:

```
PACKAGE_DEBUG_SPLIT_STYLE = 'debug-file-directory'
```

Una volta fatto ciò, possiamo installare le informazioni di debug per BusyBox. I pacchetti di debug, una volta creati, si troveranno in `build/tmp/deploy/rpm/*` sul sistema host. Individuare il file `busybox-dbg-...rpm` e copiarlo nel target. Ad esempio:

```
[trz@empanada core2]$ scp /home/trz/yocto/crownbay-tracing-dbg/build/tmp/deploy/
→rpm/core2_32/busybox-dbg-1.20.2-r2.core2_32.rpm root@192.168.1.31:
busybox-dbg-1.20.2-r2.core2_32.rpm                                100% 1826KB   1.8MB/s   ↵
→00:01
```


Ora installiamo il pacchetto RPM di debug sul sistema target:

```
root@crownbay:~# rpm -i busybox-dbg-1.20.2-r2.core2_32.rpm
```


Ora che le informazioni di debug sono installate, vediamo che le voci di BusyBox visualizzano le loro funzioni in forma simbolica:

```
File Edit View Search Terminal Help
Events: 4K cycles
+ 3.60% wget [kernel.kallsyms] [k] sub_preempt_count
+ 3.12% wget [kernel.kallsyms] [k] read_hpet
+ 2.73% wget [kernel.kallsyms] [k] add_preempt_count
+ 2.21% wget [kernel.kallsyms] [k] get_parent_ip
+ 1.94% wget [kernel.kallsyms] [k] system_call
+ 1.88% wget [kernel.kallsyms] [k] __find_get_block
+ 1.77% wget [kernel.kallsyms] [k] __copy_from_user_ll_nzero
+ 1.77% wget [kernel.kallsyms] [k] __copy_to_user_ll
+ 1.43% wget [kernel.kallsyms] [k] ext3_get_blocks_handle
+ 1.42% wget [kernel.kallsyms] [k] tcp_recvmmsg
+ 1.41% wget [kernel.kallsyms] [k] ext3_new_blocks
+ 1.34% wget [kernel.kallsyms] [k] __block_write_begin
+ 1.32% wget [kernel.kallsyms] [k] in_lock_functions
+ 1.32% wget [kernel.kallsyms] [k] ext3_mark_inode_dirty
+ 1.17% wget [kernel.kallsyms] [k] memset
+ 1.13% wget [kernel.kallsyms] [k] debug_smp_processor_id
+ 1.08% wget [kernel.kallsyms] [k] __schedule
+ 1.05% wget [kernel.kallsyms] [k] journal_add_journal_head
+ 0.92% wget [kernel.kallsyms] [k] __ext3_get_inode_loc
+ 0.83% wget [kernel.kallsyms] [k] do_sys_poll
+ 0.81% wget [kernel.kallsyms] [k] journal_dirty_metadata
+ 0.75% wget libc-2.16.so [.] 0x00115093
+ 0.74% wget [kernel.kallsyms] [k] find_busiest_group
+ 0.73% wget [kernel.kallsyms] [k] bit_waitqueue
+ 0.73% wget libc-2.16.so [.] read
- 0.67% wget busybox [.] udhcpc_main
udhcpc_main
+ 0.67% wget [kernel.kallsyms] [k] restore_nocheck
+ 0.66% wget [kernel.kallsyms] [k] radix_tree_lookup_element
+ 0.63% wget [kernel.kallsyms] [k] journal_stop
+ 0.63% wget [kernel.kallsyms] [k] kmem_cache_alloc
+ 0.62% wget [kernel.kallsyms] [k] tcp_poll
+ 0.62% wget [kernel.kallsyms] [k] do_get_write_access
+ 0.61% wget [kernel.kallsyms] [k] ext3_ordered_write_end
+ 0.61% wget libc-2.16.so [.] clearerr
+ 0.60% wget [kernel.kallsyms] [k] ext3_write_begin
+ 0.59% wget [kernel.kallsyms] [k] sched_clock_local
+ 0.58% wget [kernel.kallsyms] [k] fsnotify
+ 0.58% wget [kernel.kallsyms] [k] journal_put_journal_head
+ 0.55% wget [kernel.kallsyms] [k] __rcu_read_unlock
Press '?' for help on key bindings
```

Se espandiamo una delle voci e premiamo `Enter` su un nodo foglia, ci viene mostrato un menu di azioni che possiamo intraprendere per ottenere maggiori informazioni relative a quella voce:



Una di queste azioni ci permette di visualizzare una vista che mostra una panoramica delle funzioni profilate incentrata su BusyBox (in questo caso abbiamo anche espanso tutti i nodi usando il tasto E):



Infine, possiamo vedere che ora che le informazioni di debug di BusyBox sono installate, il simbolo precedentemente non risolto nella voce "sys\_clock\_gettime()" menzionata in precedenza è ora risolto e mostra che la chiamata di sistema sys\_clock\_gettime, che era la fonte del 6,75% dell'overhead di copy-to-user, è stata avviata dalla funzione BusyBox handle\_input():

```

trz@empanada:~
File Edit View Search Terminal Help
Events: 4K cycles
+ 1.77% wget [kernel.kallsyms] [k] __copy_from_user_ll_nozero
- 1.77% wget [kernel.kallsyms] [k] __copy_to_user_ll
  - __copy_to_user_ll
    - 90.87% copy_to_user
      - 97.79% memcpy_toiovec
        - 89.99% tcp_recvmmsg
          inet_recvmmsg
          sock_aio_read
          do_sync_read
          vfs_read
          sys_read
          syscalls
          read
        - 10.01% skb_copy_datagram_iovec
          tcp_recvmmsg
          inet_recvmmsg
          sock_aio_read
          do_sync_read
          vfs_read
          sys_read
          syscalls
          read
      + 2.21% sys_clock_gettime
      - 6.75% sys_clock_gettime
        syscalls
        syscalls
        handle_input
      - 2.38% memcpy_toiovec
        skb_copy_datagram_iovec
        tcp_recvmmsg
        inet_recvmmsg
        sock_aio_read
        do_sync_read
        vfs_read
        sys_read
        syscalls
        read
    + 1.43% wget [kernel.kallsyms] [k] ext3_get_blocks_handle
    + 1.42% wget [kernel.kallsyms] [k] tcp_recvmmsg
Press '?' for help on key bindings

```

Al livello più basso Per entrare nel dettaglio, possiamo scendere al livello assembly e vedere quali istruzioni hanno causato il maggior overhead in una funzione. Premendo Enter sulla funzione `udhcpc_main`, ci viene nuovamente mostrato un menu:

```

trz@empanada:~
File Edit View Search Terminal Help
Annotate udhcpc_main
Zoom into wget(1241) thread
Zoom out of busybox DS0
Browse map details
Exit
ESC: exit, ENTER|->: Select option

```

Selezionando `Annotate udhcpc_main`, otteniamo un elenco dettagliato delle percentuali per istruzione per la funzione `udhcpc_main`. Dal display, possiamo vedere che oltre il 50% del tempo impiegato in questa funzione è occupato da un paio di test e dallo spostamento di una costante (1) in un registro:

```

trz@empanada:~
File Edit View Search Terminal Help
udhpc_main
3.70 :      805307a:      test    %cl,%cl
7.41 :      805307c:      jne      80531aa <fchmod@plt+0x6fda>
0.00 :      8053082:      lea      0x28(%esp),%esi
0.00 :      8053086:      mov      %esi,0x18(%esp)
0.00 :      805308a:      mov      $0x1000,%edi
0.00 :      805308f:      mov      0x48(%ebx),%esi
0.00 :      8053092:      mov      0x18(%esp),%eax
3.70 :      8053096:      mov      $0x3e8,%ecx
0.00 :      805309b:      mov      $0x1,%edx
0.00 :      80530a0:      call     80ac1b5 <fchmod@plt+0x5ffe5>
11.11 :      80530a5:      test     %eax,%eax
0.00 :      80530a7:      je       80531e2 <fchmod@plt+0x7012>
0.00 :      80530ad:      mov      %ebp,(%esp)
3.70 :      80530b0:      call     804bf10 <clearerr@plt>
0.00 :      80530b5:      mov      0x80d3988,%esi
0.00 :      80530bb:      movl     $0x0,(%esi)
0.00 :      80530c1:      mov      0x1c(%esp),%esi
0.00 :      80530c5:      mov      %ebp,0xc(%esp)
3.70 :      80530c9:      mov      %edi,0x8(%esp)
0.00 :      80530cd:      movl     $0x1,0x4(%esp)
0.00 :      80530d5:      mov      %esi,(%esp)
0.00 :      80530d8:      call     804b5c0 <fread@plt>
29.63 :      80530dd:      test     %eax,%eax
0.00 :      80530df:      mov      %eax,%esi
0.00 :      80530e1:      jg       80530f8 <fchmod@plt+0x6f28>
0.00 :      80530e3:      mov      0x80d3988,%esi
0.00 :      80530e9:      cmpl     $0xb,(%esi)
0.00 :      80530ec:      jne      8053210 <fchmod@plt+0x7040>
0.00 :      80530f2:      movzbl   0x55(%ebx),%ecx
0.00 :      80530f6:      jmp      805307a <fchmod@plt+0x6eaa>
0.00 :      80530f8:      mov      0x4c(%ebx),%eax
0.00 :      80530fb:      mov      %esi,%ecx
0.00 :      80530fd:      mov      %esi,%edi
0.00 :      80530ff:      mov      0x1c(%esp),%edx
0.00 :      8053103:      sar      $0x1f,%edi
0.00 :      8053106:      call     80862ea <fchmod@plt+0x3a11a>
14.81 :      805310b:      mov      $0x1,%eax
0.00 :      8053110:      add      %esi,0x10(%ebx)
3.70 :      8053113:      adc      %edi,0x14(%ebx)
0.00 :      8053116:      call     808bfff <fchmod@plt+0x3fe2f>
0.00 :      805311b:      movzbl   0x55(%ebx),%ecx
3.70 :      805311f:      test     %cl,%cl
0.00 :      8053121:      je       805308a <fchmod@plt+0x6eba>
0.00 :      8053127:      mov      (%ebx),%eax
<- /ESC: Exit, TAB/shift+TAB: Cycle hot lines, H: Go to hottest line, -> /ENTER: L

```

Come introduzione al tracing [tracciamento], proviamo un altro profilo utilizzando un contatore diverso, diverso dal valore predefinito `cycles`.

L'infrastruttura di tracing e profilazione in Linux si è unificata in modo tale da consentirci di utilizzare lo stesso strumento con un set di contatori completamente diverso, non solo con i contatori hardware standard a cui gli strumenti tradizionali erano costretti a limitarsi (gli strumenti tradizionali ora possono effettivamente sfruttare le maggiori possibilità a loro disposizione e, in alcuni casi, lo hanno già fatto, come accennato in precedenza).

Possiamo ottenere un elenco degli eventi disponibili che possono essere utilizzati per profilare un carico di lavoro tramite `perf list`:

```
root@crownbay:~# perf list
```

List of pre-defined events (to be used **in** `-e`):

|                                                                           |                  |
|---------------------------------------------------------------------------|------------------|
| <code>cpu-cycles</code> OR <code>cycles</code>                            | [Hardware event] |
| <code>stalled-cycles-frontend</code> OR <code>idle-cycles-frontend</code> | [Hardware event] |
| <code>stalled-cycles-backend</code> OR <code>idle-cycles-backend</code>   | [Hardware event] |
| <code>instructions</code>                                                 | [Hardware event] |
| <code>cache-references</code>                                             | [Hardware event] |
| <code>cache-misses</code>                                                 | [Hardware event] |

(continues on next page)

(continua dalla pagina precedente)

|                                                                                   |                                 |
|-----------------------------------------------------------------------------------|---------------------------------|
| branch-instructions OR branches                                                   | [Hardware event]                |
| branch-misses                                                                     | [Hardware event]                |
| bus-cycles                                                                        | [Hardware event]                |
| ref-cycles                                                                        | [Hardware event]                |
| cpu-clock                                                                         | [Software event]                |
| task-clock                                                                        | [Software event]                |
| page-faults OR faults                                                             | [Software event]                |
| minor-faults                                                                      | [Software event]                |
| major-faults                                                                      | [Software event]                |
| context-switches OR cs                                                            | [Software event]                |
| cpu-migrations OR migrations                                                      | [Software event]                |
| alignment-faults                                                                  | [Software event]                |
| emulation-faults                                                                  | [Software event]                |
| L1-dcache-loads                                                                   | [Hardware cache event]          |
| L1-dcache-load-misses                                                             | [Hardware cache event]          |
| L1-dcache-prefetch-misses                                                         | [Hardware cache event]          |
| L1-icache-loads                                                                   | [Hardware cache event]          |
| L1-icache-load-misses                                                             | [Hardware cache event]          |
| .                                                                                 |                                 |
| .                                                                                 |                                 |
| .                                                                                 |                                 |
| rNNN                                                                              | [Raw hardware event descriptor] |
| cpu/t1=v1[,t2=v2,t3 ...]/modifier<br>(see 'perf list --help' on how to encode it) | [Raw hardware event descriptor] |
| mem:<addr>[:access]                                                               | [Hardware breakpoint]           |
| sunrpc:rpc_call_status                                                            | [Tracepoint event]              |
| sunrpc:rpc_bind_status                                                            | [Tracepoint event]              |
| sunrpc:rpc_connect_status                                                         | [Tracepoint event]              |
| sunrpc:rpc_task_begin                                                             | [Tracepoint event]              |
| skb:kfree_skb                                                                     | [Tracepoint event]              |
| skb:consume_skb                                                                   | [Tracepoint event]              |
| skb:skb_copy_datagram_iovec                                                       | [Tracepoint event]              |
| net:net_dev_xmit                                                                  | [Tracepoint event]              |
| net:net_dev_queue                                                                 | [Tracepoint event]              |
| net:netif_receive_skb                                                             | [Tracepoint event]              |
| net:netif_rx                                                                      | [Tracepoint event]              |
| napi:napi_poll                                                                    | [Tracepoint event]              |
| sock:sock_rcvqueue_full                                                           | [Tracepoint event]              |
| sock:sock_exceed_buf_limit                                                        | [Tracepoint event]              |

(continues on next page)

(continua dalla pagina precedente)

|                                          |                    |
|------------------------------------------|--------------------|
| udp:udp_fail_queue_rcv_skb               | [Tracepoint event] |
| hda:hda_send_cmd                         | [Tracepoint event] |
| hda:hda_get_response                     | [Tracepoint event] |
| hda:hda_bus_reset                        | [Tracepoint event] |
| scsi:scsi_dispatch_cmd_start             | [Tracepoint event] |
| scsi:scsi_dispatch_cmd_error             | [Tracepoint event] |
| scsi:scsi_eh_wakeup                      | [Tracepoint event] |
| drm:drm_vblank_event                     | [Tracepoint event] |
| drm:drm_vblank_event_queued              | [Tracepoint event] |
| drm:drm_vblank_event_delivered           | [Tracepoint event] |
| random:mix_pool_bytes                    | [Tracepoint event] |
| random:mix_pool_bytes_nolock             | [Tracepoint event] |
| random:credit_entropy_bits               | [Tracepoint event] |
| gpio:gpio_direction                      | [Tracepoint event] |
| gpio:gpio_value                          | [Tracepoint event] |
| block:block_rq_abort                     | [Tracepoint event] |
| block:block_rq_requeue                   | [Tracepoint event] |
| block:block_rq_issue                     | [Tracepoint event] |
| block:block_bio_bounce                   | [Tracepoint event] |
| block:block_bio_complete                 | [Tracepoint event] |
| block:block_bio_backmerge                | [Tracepoint event] |
| .                                        |                    |
| .                                        |                    |
| writeback:writeback_wake_thread          | [Tracepoint event] |
| writeback:writeback_wake_forker_thread   | [Tracepoint event] |
| writeback:writeback_bdi_register         | [Tracepoint event] |
| .                                        |                    |
| .                                        |                    |
| writeback:writeback_single_inode_requeue | [Tracepoint event] |
| writeback:writeback_single_inode         | [Tracepoint event] |
| kmem:kmalloc                             | [Tracepoint event] |
| kmem:kmem_cache_alloc                    | [Tracepoint event] |
| kmem:mm_page_alloc                       | [Tracepoint event] |
| kmem:mm_page_alloc_zone_locked           | [Tracepoint event] |
| kmem:mm_page_pcpu_drain                  | [Tracepoint event] |
| kmem:mm_page_alloc_extfrag               | [Tracepoint event] |
| vmscan:mm_vmscan_kswapd_sleep            | [Tracepoint event] |
| vmscan:mm_vmscan_kswapd_wake             | [Tracepoint event] |
| vmscan:mm_vmscan_wakeup_kswapd           | [Tracepoint event] |
| vmscan:mm_vmscan_direct_reclaim_begin    | [Tracepoint event] |
| .                                        |                    |
| .                                        |                    |
| module:module_get                        | [Tracepoint event] |

(continues on next page)



(continua dalla pagina precedente)

|                                 |                    |
|---------------------------------|--------------------|
| module:module_put               | [Tracepoint event] |
| module:module_request           | [Tracepoint event] |
| sched:sched_kthread_stop        | [Tracepoint event] |
| sched:sched_wakeup              | [Tracepoint event] |
| sched:sched_wakeup_new          | [Tracepoint event] |
| sched:sched_process_fork        | [Tracepoint event] |
| sched:sched_process_exec        | [Tracepoint event] |
| sched:sched_stat_runtime        | [Tracepoint event] |
| rcu:rcu_utilization             | [Tracepoint event] |
| workqueue:workqueue_queue_work  | [Tracepoint event] |
| workqueue:workqueue_execute_end | [Tracepoint event] |
| signal:signal_generate          | [Tracepoint event] |
| signal:signal_deliver           | [Tracepoint event] |
| timer:timer_init                | [Tracepoint event] |
| timer:timer_start               | [Tracepoint event] |
| timer:hrtimer_cancel            | [Tracepoint event] |
| timer:itimer_state              | [Tracepoint event] |
| timer:itimer_expire             | [Tracepoint event] |
| irq:irq_handler_entry           | [Tracepoint event] |
| irq:irq_handler_exit            | [Tracepoint event] |
| irq:softirq_entry               | [Tracepoint event] |
| irq:softirq_exit                | [Tracepoint event] |
| irq:softirq_raise               | [Tracepoint event] |
| printk:console                  | [Tracepoint event] |
| task:task_newtask               | [Tracepoint event] |
| task:task_rename                | [Tracepoint event] |
| syscalls:sys_enter_socketcall   | [Tracepoint event] |
| syscalls:sys_exit_socketcall    | [Tracepoint event] |
| .                               |                    |
| .                               |                    |
| .                               |                    |
| syscalls:sys_enter_unshare      | [Tracepoint event] |
| syscalls:sys_exit_unshare       | [Tracepoint event] |
| raw_syscalls:sys_enter          | [Tracepoint event] |
| raw_syscalls:sys_exit           | [Tracepoint event] |

**i Unire il Tutto**

Si tratta esattamente dello stesso set di eventi definito dal sottosistema degli eventi di tracciamento ed esposto da ftrace / trace-cmd / KernelShark come file in `/sys/kernel/debug/tracing/events`, da SystemTap come `kernel.trace("tracepoint_name")` e (parzialmente) accessibile da LTTng.

Solo un sottoinsieme di questi sarebbe di nostro interesse quando esaminiamo questo carico di lavoro, quindi scegliamo i sottosistemi più probabili (identificati dalla stringa prima dei due punti negli eventi Tracepoint) ed eseguiamo un `perf stat` utilizzando solo i caratteri jolly di questi sottosistemi:

```
root@crownbay:~# perf stat -e skb:* -e net:* -e napi:* -e sched:* -e workqueue:* -
↪e irq:* -e syscalls:* wget https://downloads.yoctoproject.org/mirror/sources/
↪linux-2.6.19.2.tar.bz2
Performance counter stats for 'wget https://downloads.yoctoproject.org/mirror/
↪sources/linux-2.6.19.2.tar.bz2':
```

```

23323 skb:kfree_skb
      0 skb:consume_skb
49897 skb:skb_copy_datagram_iovec
6217 net:net_dev_xmit
6217 net:net_dev_queue
7962 net:netif_receive_skb
      2 net:netif_rx
8340 napi:napi_poll
      0 sched:sched_kthread_stop
      0 sched:sched_kthread_stop_ret
3749 sched:sched_wakeup
      0 sched:sched_wakeup_new
      0 sched:sched_switch
29 sched:sched_migrate_task
      0 sched:sched_process_free
1 sched:sched_process_exit
      0 sched:sched_wait_task
      0 sched:sched_process_wait
      0 sched:sched_process_fork
1 sched:sched_process_exec
      0 sched:sched_stat_wait
2106519415641 sched:sched_stat_sleep
      0 sched:sched_stat_iowait
147453613 sched:sched_stat_blocked
12903026955 sched:sched_stat_runtime
      0 sched:sched_pi_setprio
3574 workqueue:workqueue_queue_work
3574 workqueue:workqueue_activate_work
```

(continues on next page)

(continua dalla pagina precedente)

```

    0 workqueue:workqueue_execute_start
    0 workqueue:workqueue_execute_end
16631 irq:irq_handler_entry
16631 irq:irq_handler_exit
28521 irq:softirq_entry
28521 irq:softirq_exit
28728 irq:softirq_raise
    1 syscalls:sys_enter_sendmmsg
    1 syscalls:sys_exit_sendmmsg
    0 syscalls:sys_enter_recvmmsg
    0 syscalls:sys_exit_recvmmsg
   14 syscalls:sys_enter_socketcall
   14 syscalls:sys_exit_socketcall
    .
    .
    .
16965 syscalls:sys_enter_read
16965 syscalls:sys_exit_read
12854 syscalls:sys_enter_write
12854 syscalls:sys_exit_write
    .
    .
    .

58.029710972 seconds time elapsed


```

Scegliamo uno di questi tracepoint e diciamo a perf di eseguire un profilo utilizzandolo come evento di campionamento:

```

root@crownbay:~# perf record -g -e sched:sched_wakeup wget https://downloads.
↳yoctoproject.org/mirror/sources/linux-2.6.19.2.tar.bz2

```



Lo screenshot qui sopra mostra i risultati dell'esecuzione di un profilo utilizzando il tracepoint sched:sched\_switch, che mostra i costi relativi dei vari percorsi verso sched\_wakeup (si noti che sched\_wakeup è il nome del tracepoint: è effettivamente definito all'interno di ttwu\_do\_wakeup(), il che spiega il nome della funzione effettivamente visualizzato nel profilo):

```
/*
 * Mark the task runnable and perform wakeup-preemption.
 */
static void
ttwu_do_wakeup(struct rq *rq, struct task_struct *p, int wake_flags)
{
    trace_sched_wakeup(p, true);
    .
    .
    .
}
```

Un paio delle catene di chiamate più interessanti sono espansive e visualizzate sopra, in pratica alcuni percorsi di ricezione di rete che presumibilmente finiscono per risvegliare wget (BusyBox) quando i dati di rete sono pronti [ready].

Si noti che, poiché i tracepoint vengono normalmente utilizzati per il tracing, il periodo di campionamento predefinito per i tracepoint è 1, ovvero perf effettuerà un campionamento a ogni occorrenza dell'evento (questo valore può essere modificato utilizzando l'opzione `-c`). Ciò è in contrasto con i contatori hardware, come ad esempio il contatore hardware predefinito `cycles` utilizzato per la normale profilazione, dove i periodi di campionamento sono molto più elevati (nell'ordine delle migliaia) perché la profilazione dovrebbe avere un overhead il più basso possibile e il campionamento a ogni ciclo sarebbe eccessivamente oneroso.

## Utilizzo di perf per il Tracing di Base

La profilazione è un ottimo strumento per risolvere molti problemi o per ottenere una visione d'insieme di ciò che accade a un carico di lavoro o all'interno del sistema. Tuttavia, per definizione, si tratta di un'approssimazione, come suggerisce il termine più importante ad essa associato: `sampling` [campionamento]. Da un lato, consente di ottenere un'immagine rappresentativa di ciò che accade nel sistema in modo economico, ma dall'altro, questa economicità ne limita l'utilità quando i dati suggeriscono la necessità di un'analisi più approfondita per scoprire cosa sta realmente accadendo. In questi casi, l'unico modo per capire cosa sta realmente succedendo è analizzare (o riassumere in modo più intelligente) i singoli passaggi che contribuiscono al comportamento di livello superiore rivelato dai dati di profilazione a grana grossa.

A titolo di esempio concreto, possiamo tracciare tutti gli eventi che riteniamo pertinenti al nostro carico di lavoro:

```
root@crownbay:~# perf record -g -e skb:* -e net:* -e napi:* -e sched:sched_switch -
↪e sched:sched_wakeup -e irq:*
-e syscalls:sys_enter_read -e syscalls:sys_exit_read -e syscalls:sys_enter_write -
↪e syscalls:sys_exit_write
wget https://downloads.yoctoproject.org/mirror/sources/linux-2.6.19.2.tar.bz2
```

Possiamo visualizzare l'output di traccia grezzo utilizzando `perf script` senza argomenti:

```
root@crownbay:~# perf script

perf 1262 [000] 11624.857082: sys_exit_read: 0x0
perf 1262 [000] 11624.857193: sched_wakeup: comm=migration/0 pid=6 prio=0
↪success=1 target_cpu=000
wget 1262 [001] 11624.858021: softirq_raise: vec=1 [action=TIMER]
wget 1262 [001] 11624.858074: softirq_entry: vec=1 [action=TIMER]
wget 1262 [001] 11624.858081: softirq_exit: vec=1 [action=TIMER]
wget 1262 [001] 11624.858166: sys_enter_read: fd: 0x0003, buf: 0xbf82c940,
↪count: 0x0200
wget 1262 [001] 11624.858177: sys_exit_read: 0x200
wget 1262 [001] 11624.858878: kfree_skb: skbaddr=0xeb248d80 protocol=0
↪location=0xc15a5308
wget 1262 [001] 11624.858945: kfree_skb: skbaddr=0xeb248000 protocol=0
↪location=0xc15a5308
```

(continues on next page)

(continua dalla pagina precedente)

```

wget 1262 [001] 11624.859020: softirq_raise: vec=1 [action=TIMER]
wget 1262 [001] 11624.859076: softirq_entry: vec=1 [action=TIMER]
wget 1262 [001] 11624.859083: softirq_exit: vec=1 [action=TIMER]
wget 1262 [001] 11624.859167: sys_enter_read: fd: 0x0003, buf: 0xb7720000, ↵
↪count: 0x0400
wget 1262 [001] 11624.859192: sys_exit_read: 0x1d7
wget 1262 [001] 11624.859228: sys_enter_read: fd: 0x0003, buf: 0xb7720000, ↵
↪count: 0x0400
wget 1262 [001] 11624.859233: sys_exit_read: 0x0
wget 1262 [001] 11624.859573: sys_enter_read: fd: 0x0003, buf: 0xbf82c580, ↵
↪count: 0x0200
wget 1262 [001] 11624.859584: sys_exit_read: 0x200
wget 1262 [001] 11624.859864: sys_enter_read: fd: 0x0003, buf: 0xb7720000, ↵
↪count: 0x0400
wget 1262 [001] 11624.859888: sys_exit_read: 0x400
wget 1262 [001] 11624.859935: sys_enter_read: fd: 0x0003, buf: 0xb7720000, ↵
↪count: 0x0400
wget 1262 [001] 11624.859944: sys_exit_read: 0x400

```

Questo ci fornisce una sequenza dettagliata e con timestamp degli eventi che si sono verificati all'interno del carico di lavoro in relazione a tali eventi.

Per molti aspetti, la profilazione può essere considerata un sottoinsieme del tracing: teoricamente, se si dispone di un insieme di eventi di tracing sufficiente a catturare tutti gli aspetti importanti di un carico di lavoro, è possibile ricavare qualsiasi risultato o visualizzazione ottenibile con un'esecuzione di profilazione.

Un altro aspetto della profilazione tradizionale è che, pur essendo potente sotto molti punti di vista, è limitata dalla granularità dei dati sottostanti. Gli strumenti di profilazione offrono vari modi per ordinare e presentare i dati di esempio, rendendoli molto più utili e adatti alla sperimentazione da parte dell'utente, ma in definitiva non possono essere utilizzati in modo aperto per estrarre dati che semplicemente non sono presenti, poiché concettualmente la maggior parte di essi viene scartata.

I dati di tracciamento dettagliati e completi offrono tuttavia l'opportunità di manipolare e presentare le informazioni raccolte durante un'esecuzione di tracciamento in un'infinità di modi.

Un altro modo di vedere la cosa è che i contatori 'primitive' possono essere utilizzati solo in un numero limitato di modi per generare output interessanti; per ottenere qualcosa di più complesso di un semplice conteggio è necessaria una certa quantità di logica aggiuntiva, che in genere è specifica per il problema in questione. Ad esempio, se volessimo utilizzare un 'counter' che corrisponda al valore della differenza di tempo tra il momento in cui un processo è stato programmato per essere eseguito su un processore e il momento in cui è stato effettivamente eseguito, non ci aspetteremmo che un tale contatore esista di per sé, ma potremmo derivarne uno chiamato, ad esempio, `wake-up_latency` e usarlo per estrarre una visione utile di quella metrica dai dati di tracciamento. Allo stesso modo, non possiamo davvero capire con i normali strumenti di profilazione quanti dati ogni processo sul sistema legge e scrive, né quante di queste operazioni di lettura e scrittura falliscono completamente. Se disponessimo di dati di tracciamento sufficienti, con gli strumenti giusti potremmo facilmente estrarre e presentare tali informazioni, ma per farlo avremmo bisogno di qualcosa di diverso dai semplici strumenti di profilazione preconfezionati.

Fortunatamente, esiste un modo generico per gestire tali esigenze, chiamato "programming languages" [linguaggi di programmazione]. Rendere i linguaggi di programmazione facilmente disponibili per l'applicazione a tali problemi, dato lo specifico formato dei dati, è chiamato 'programming language binding' per quei dati e quel linguaggio. perf supporta due binding di linguaggi di programmazione, uno per Python e uno per Perl.

### Unire il Tutto

I binding di linguaggio per la manipolazione e l'aggregazione dei dati di tracciamento non sono certo un'idea nuova. Uno dei primi progetti a farlo è stato il compilatore dpcc DProbes di IBM, un compilatore ANSI C che si rivolgeva a un linguaggio assembly di basso livello in esecuzione su un interprete in-kernel del sistema target. Questo è esattamente analogo a ciò che faceva DTrace di Sun, con la differenza che DTrace ha inventato un proprio linguaggio per questo scopo. SystemTap, fortemente ispirato a DTrace, ha creato un proprio linguaggio proprietario, ma anziché eseguire il prodotto su un interprete integrato nel kernel, ha sviluppato un complesso meccanismo basato su un compilatore per tradurre il linguaggio in moduli del kernel scritti in C.

Ora che abbiamo i dati di traccia in `perf.data`, possiamo usare `perf script -g` per generare uno script di base con gestori per gli eventi di lettura/scrittura in entrata/uscita che abbiamo registrato:

```
root@crownbay:~# perf script -g python
generated Python script: perf-script.py
```

Lo script di base crea semplicemente una funzione Python per ogni tipo di evento presente nel file `perf.data`. Il corpo di ogni funzione si limita a stampare il nome dell'evento insieme ai suoi parametri. Ad esempio:

```
def net__netif_rx(event_name, context, common_cpu,
    common_secs, common_nsecs, common_pid, common_comm,
    skbaddr, len, name):
    print_header(event_name, common_cpu, common_secs, common_nsecs,
        common_pid, common_comm)

    print "skbaddr=%u, len=%u, name=%s\n" % (skbaddr, len, name),
```

Possiamo eseguire direttamente questo script per stampare tutti gli eventi contenuti nel file `perf.data`:

```
root@crownbay:~# perf script -s perf-script.py

in trace_begin
syscalls__sys_exit_read      0 11624.857082795      1262 perf          nr=3,
↳ret=0
sched__sched_wakeup         0 11624.857193498      1262 perf          ↳
↳comm=migration/0, pid=6, prio=0, success=1, target_cpu=0
irq__softirq_raise          1 11624.858021635      1262 wget          vec=TIMER
irq__softirq_entry           1 11624.858074075      1262 wget          vec=TIMER
irq__softirq_exit            1 11624.858081389      1262 wget          vec=TIMER
syscalls__sys_enter_read     1 11624.858166434      1262 wget          nr=3,
(continues on next page)
```

(continua dalla pagina precedente)

```

↪ fd=3, buf=3213019456, count=512
syscalls__sys_exit_read      1 11624.858177924      1262 wget      nr=3, ↪
↪ ret=512
skb_kfree_skb               1 11624.858878188      1262 wget      ↪
↪ skbaddr=3945041280, location=3243922184, protocol=0
skb_kfree_skb               1 11624.858945608      1262 wget      ↪
↪ skbaddr=3945037824, location=3243922184, protocol=0
irq__softirq_raise          1 11624.859020942      1262 wget      vec=TIMER
irq__softirq_entry           1 11624.859076935      1262 wget      vec=TIMER
irq__softirq_exit            1 11624.859083469      1262 wget      vec=TIMER
syscalls__sys_enter_read     1 11624.859167565      1262 wget      nr=3,
↪ fd=3, buf=3077701632, count=1024
syscalls__sys_exit_read     1 11624.859192533      1262 wget      nr=3, ↪
↪ ret=471
syscalls__sys_enter_read     1 11624.859228072      1262 wget      nr=3,
↪ fd=3, buf=3077701632, count=1024
syscalls__sys_exit_read     1 11624.859233707      1262 wget      nr=3, ↪
↪ ret=0
syscalls__sys_enter_read     1 11624.859573008      1262 wget      nr=3,
↪ fd=3, buf=3213018496, count=512
syscalls__sys_exit_read     1 11624.859584818      1262 wget      nr=3, ↪
↪ ret=512
syscalls__sys_enter_read     1 11624.859864562      1262 wget      nr=3,
↪ fd=3, buf=3077701632, count=1024
syscalls__sys_exit_read     1 11624.859888770      1262 wget      nr=3, ↪
↪ ret=1024
syscalls__sys_enter_read     1 11624.859935140      1262 wget      nr=3,
↪ fd=3, buf=3077701632, count=1024
syscalls__sys_exit_read     1 11624.859944032      1262 wget      nr=3, ↪
↪ ret=1024

```

Questo di per sé non è molto utile; dopotutto, possiamo ottenere praticamente lo stesso risultato eseguendo perf script senza argomenti nella stessa directory del file perf.data.

Possiamo tuttavia sostituire le istruzioni print nei corpi delle funzioni generate con qualsiasi cosa desideriamo, rendendole così infinitamente più utili.

A titolo di semplice esempio, sostituiamo le istruzioni print nei corpi delle funzioni con una semplice funzione che non fa altro che incrementare un contatore per ogni evento. Quando il programma viene eseguito su un file perf.data, ogni volta che viene rilevato un particolare evento, il contatore corrispondente viene incrementato. Ad esempio:

```

def net__netif_rx(event_name, context, common_cpu,
                  common_secs, common_nsecs, common_pid, common_comm,
                  skbaddr, len, name):
    inc_counts(event_name)

```



Ogni funzione di gestione degli eventi nel codice generato viene modificata per fare ciò. Per comodità, definiamo una funzione comune chiamata `inc_counts()` che viene richiamata da ogni gestore; `inc_counts()` si limita a contare ogni evento utilizzando l'hash `counts`, una funzione hash specializzata che esegue l'autovivificazione in stile Perl, una funzionalità estremamente utile per i tipi di aggregazione multilivello comunemente utilizzati nell'elaborazione delle tracce (vedere la documentazione di `perf` sul binding per il linguaggio Python per i dettagli):

```
counts = autodict()

def inc_counts(event_name):
    try:
        counts[event_name] += 1
    except TypeError:
        counts[event_name] = 1
```

Infine, al termine dell'esecuzione dell'elaborazione della traccia, vogliamo stampare il risultato di tutti i conteggi per evento. A tale scopo, utilizziamo la funzione speciale `trace_end()`:

```
def trace_end():
    for event_name, count in counts.iteritems():
        print "%-40s %10s\n" % (event_name, count)
```

Il risultato finale è un riepilogo di tutti gli eventi registrati nella traccia:

```
skb__skb_copy_datagram_iovec          13148
irq__softirq_entry                    4796
irq__irq_handler_exit                 3805
irq__softirq_exit                     4795
syscalls__sys_enter_write             8990
net__net_dev_xmit                     652
skb__kfree_skb                        4047
sched__sched_wakeup                   1155
irq__irq_handler_entry                3804
irq__softirq_raise                    4799
net__net_dev_queue                    652
syscalls__sys_enter_read              17599
net__netif_receive_skb                1743
syscalls__sys_exit_read               17598
net__netif_rx                         2
napi__napi_poll                       1877
syscalls__sys_exit_write              8990
```

Si noti che si tratta praticamente delle stesse informazioni che otteniamo da `perf stat`, il che supporta in parte l'idea menzionata in precedenza, ovvero che, con i dati di traccia appropriati, è possibile ricavare da essi riepiloghi di profilazione di livello superiore.

Documentazione sull'utilizzo di *'perf script' Python binding*.

## Tracing e Profilazione a Livello di Sistema

Gli esempi finora presentati si sono concentrati sul tracciamento di un programma o di un carico di lavoro specifico: in altre parole, ogni esecuzione di profilazione ha specificato il programma da profilare nella riga di comando, ad esempio `perf record wget ....`.

È anche possibile, e in molti casi più interessante, eseguire un profilo o un tracciamento a livello di sistema mentre il carico di lavoro viene eseguito in una shell separata.

Per eseguire il tracciamento o la profilazione a livello di sistema, si utilizza in genere l'opzione `-a` con `perf record`.

Per dimostrarlo, aprire una finestra e avviare il profilo utilizzando il flag `-a` (premere `Ctrl-C` per interrompere il tracing):

```
root@crownbay:~# perf record -g -a
^C[ perf record: Woken up 6 times to write data ]
[ perf record: Captured and wrote 1.400 MB perf.data (~61172 samples) ]
```

In un'altra finestra, eseguire il test `wget`:

```
root@crownbay:~# wget https://downloads.yoctoproject.org/mirror/sources/linux-2.6.
↪19.2.tar.bz2
Connecting to downloads.yoctoproject.org (140.211.169.59:80)
linux-2.6.19.2.tar.b 100% \|*****\| 41727k 0:00:00 ETA
```

Qui vediamo voci non solo per il carico di `wget`, ma anche per altri processi in esecuzione sul sistema:

```

trz@empanada:~/kdev/tip
File Edit View Search Terminal Help
Events: 11K cycles
+ 8.05% swapper [kernel.kallsyms] [k] intel_idle
- 6.04% Xorg libc-2.16.so [.] memset
- memset
- 58.17% SGXQueueTransfer
  0xb767fb
  - PVR2DBlt
    70.54% 0xb76abf
    29.46% 0xb76ac1
  - 41.83% 0xb767f6
    PVR2DBlt
    0xb76abf
+ 3.61% swapper [kernel.kallsyms] [k] read_hpet
+ 1.93% swapper [kernel.kallsyms] [k] ioread32
+ 1.21% Xorg [kernel.kallsyms] [k] ohci_irq
+ 0.73% swapper [kernel.kallsyms] [k] debug_smp_p
+ 0.70% swapper [kernel.kallsyms] [k] menu_select
+ 0.69% swapper [kernel.kallsyms] [k] ohci_irq
+ 0.57% swapper [kernel.kallsyms] [k] sub_preempt
- 0.53% wget [kernel.kallsyms] [k] memset
- memset
+ 88.85% __block_write_begin
+ 8.22% alloc_buffer_head
- 1.65% kmem_cache_alloc
  alloc_buffer_head
  alloc_page_buffers
  create_empty_buffers
  __block_write_begin
  ext4_da_write_begin
  generic_file_buffered_write
  __generic_file_aio_write
  generic_file_aio_write
  ext4_file_write
  do_sync_write
  vfs_write
  sys_write
  syscall_call
  GI__libc_write
+ 1.27% kmem_cache_alloc_trace
+ 0.51% swapper [kernel.kallsyms] [k] add_preempt
+ 0.49% Xorg [kernel.kallsyms] [k] read_hpet
+ 0.49% Xorg [emgd] [k] igd_alter_c
+ 0.48% wget [kernel.kallsyms] [k] read_hpet
+ 0.47% wget [kernel.kallsyms] [k] __copy_to_u
+ 0.45% swapper [kernel.kallsyms] [k] __raw_spin_l
+ 0.45% wget [kernel.kallsyms] [k] sub_preempt
Press '?' for help on key bindings

```

Nell'immagine qui sopra, possiamo vedere catene di chiamate che hanno origine in `libc` e una catena di chiamate da `Xorg` che dimostra che stiamo usando un driver X proprietario nello spazio utente (notare la presenza di `PVR` e di altri simboli non risolvibili nella catena di chiamate `Xorg` espansa).

Notare inoltre che nell'immagine qui sopra sono presenti voci sia per lo spazio kernel che per lo spazio utente. Possiamo anche indicare a `perf` di concentrarsi sullo spazio utente, fornendo un modificatore, in questo caso `u`, al contatore hardware `cycles` durante la registrazione di un profilo:

```

root@crownbay:~# perf record -g -a -e cycles:u
^C[ perf record: Woken up 2 times to write data ]
[ perf record: Captured and wrote 0.376 MB perf.data (~16443 samples) ]

```

```

trz@empanada:~/kdev/tip
File Edit View Search Terminal Help
Events: 4K cycles
- 12.84% wget [kernel.kallsyms] [k] system_call
  - system_call
    39.73% __read_nocancel
    20.38% __GI___libc_poll
    19.90% syscall
    19.66% __GI___libc_write
  + 7.01% wget busybox [.] retrieve_file_data
  + 5.71% wget libc-2.16.so [.] __IO_file_xsgetn
  + 4.49% wget libc-2.16.so [.] __IO_fread
  + 4.36% wget libc-2.16.so [.] clearerr
  + 3.84% wget libc-2.16.so [.] __GI___libc_poll
  + 3.69% wget libc-2.16.so [.] __read_nocancel
  + 3.42% wget busybox [.] progress_meter
  + 3.16% wget libc-2.16.so [.] syscall
  + 3.11% wget busybox [.] safe_poll
  + 3.04% wget libc-2.16.so [.] __underflow
  + 2.95% wget libc-2.16.so [.] __IO_file_underflow@@
  + 2.95% wget libc-2.16.so [.] __GI___libc_write
  + 2.55% wget busybox [.] bb_progress_update
  + 2.54% wget busybox [.] 0x00004f10
  + 2.32% wget libc-2.16.so [.] __x86.get_pc_thunk.b
  - __x86.get_pc_thunk.bx
    - 68.83% fprintf
      progress_meter
    - 31.17% buffered_vfprintf
      fprintf
      progress_meter
  + 1.79% wget busybox [.] xwrite
  + 1.71% wget busybox [.] full_write
  + 1.65% wget libc-2.16.so [.] __IO_file_read
  + 1.57% wget libc-2.16.so [.] __IO_sgetn
  + 1.43% wget busybox [.] safe_write
  + 1.09% wget libc-2.16.so [.] __GI___libc_read
  + 0.85% wget libc-2.16.so [.] __IO_switch_to_get_m
  + 0.80% dropbear dropbearmulti [.] rijndael_ecb_encrypt
  + 0.78% perf perf [.] hex2u64
  + 0.71% dropbear dropbearmulti [.] md5_compress
  + 0.60% wget busybox [.] monotonic_sec
  + 0.57% dropbear libc-2.16.so [.] __int_free
  + 0.57% wget busybox [.] get_mono
  + 0.55% dropbear dropbearmulti [.] sha1_compress
  + 0.39% perf libc-2.16.so [.] __x86.get_pc_thunk.b
  + 0.38% dropbear libc-2.16.so [.] __int_malloc
  + 0.36% wget libc-2.16.so [.] vfprintf
  + 0.36% wget libc-2.16.so [.] 0x000c9ab4
Press '?' for help on key bindings

```

Nella schermata precedente, notiamo che vengono visualizzate solo le voci relative allo spazio utente ([.])

Infine, possiamo premere **Enter** su un nodo foglia e selezionare la voce di menu **Zoom into DSO** per visualizzare solo le voci associate a uno specifico DSO. Nella schermata seguente, abbiamo ingrandito il DSO `libc`, che mostra tutte le voci associate al DSO `libc-xxx.so`.

```

trz@empanada:~/kdev/tip
File Edit View Search Terminal Help
Events: 1K cycles, DSO: libc-2.16.so
- 60.86% Xorg [.] memset
- memset
- 58.17% SGXQueueTransfer
  0xb767fb
- PVR2DBlt
  70.54% 0xb76abf
  29.46% 0xb76ac1
- 41.83% 0xb767f6
  PVR2DBlt
  0xb76abf
- 2.61% pcmanfm [.] strcmp
- strcmp
+ 50.21% __gconv_find_transform
  49.79% __dcgettext
- 2.08% pcmanfm [.] _int_malloc
  _int_malloc
- 1.92% Xorg [.] _int_malloc
  _int_malloc
- 1.49% Xorg [.] memcpy
- memcpy
- 100.00% SGXQueueTransfer
  0xb767fb
  PVR2DBlt
  0xb76abf
+ 1.29% wget [.] __GI__libc_poll
+ 1.06% wget [.] __read_nocancel
+ 0.97% wget [.] _IO_file_xsgetn
+ 0.93% wget [.] clearerr
+ 0.90% wget [.] syscall
+ 0.79% pcmanfm [.] malloc
+ 0.73% leafpad [.] strcmp
+ 0.70% wget [.] __underflow
+ 0.68% Xorg [.] _int_free
+ 0.64% pcmanfm [.] memcpy
+ 0.61% wget [.] _IO_fread
+ 0.60% leafpad [.] _int_malloc
+ 0.59% Xorg [.] free
+ 0.49% Xorg [.] __select
+ 0.49% pcmanfm [.] __x86.get_pc_thunk.bx
+ 0.47% pcmanfm [.] memset
+ 0.46% slant [.] strcmp
+ 0.44% wget [.] __x86.get_pc_thunk.bx
+ 0.44% matchbox-deskto [.] memcpy
+ 0.39% slant [.] __x86.get_pc_thunk.bx
+ 0.38% matchbox-deskto [.] _int_malloc
Press '?' for help on key bindings

```

Possiamo anche utilizzare l'opzione `-a` a livello di sistema per eseguire il tracciamento a livello di sistema. Qui tratteremo un paio di eventi dello scheduler:

```

root@crownbay:~# perf record -a -e sched:sched_switch -e sched:sched_wakeup
^C[ perf record: Woken up 38 times to write data ]
[ perf record: Captured and wrote 9.780 MB perf.data (~427299 samples) ]

```

Possiamo visualizzare l'output grezzo utilizzando `perf script` senza argomenti:

```

root@crownbay:~# perf script

perf 1383 [001] 6171.460045: sched_wakeup: comm=kworker/1:1 pid=21
↳prio=120 success=1 target_cpu=001
perf 1383 [001] 6171.460066: sched_switch: prev_comm=perf prev_
↳pid=1383 prev_prio=120 prev_state=R==> next_comm=kworker/1:1 next_pid=21 next_
↳prio=120
kworker/1:1 21 [001] 6171.460093: sched_switch: prev_comm=kworker/1:1 prev_
↳pid=21 prev_prio=120 prev_state=S==> next_comm=perf next_pid=1383 next_prio=120
swapper 0 [000] 6171.468063: sched_wakeup: comm=kworker/0:3 pid=1209

```

(continues on next page)

(continua dalla pagina precedente)

```

↪prio=120 success=1 target_cpu=000
    swapper      0 [000]   6171.468107: sched_switch: prev_comm=swapper/0 prev_
↪pid=0 prev_prio=120 prev_state=R ==> next_comm=kworker/0:3 next_pid=1209 next_
↪prio=120
    kworker/0:3  1209 [000]   6171.468143: sched_switch: prev_comm=kworker/0:3 prev_
↪pid=1209 prev_prio=120 prev_state=S ==> next_comm=swapper/0 next_pid=0 next_
↪prio=120
    perf  1383 [001]   6171.470039: sched_wakeup: comm=kworker/1:1 pid=21_
↪prio=120 success=1 target_cpu=001
    perf  1383 [001]   6171.470058: sched_switch: prev_comm=perf prev_
↪pid=1383 prev_prio=120 prev_state=R+ ==> next_comm=kworker/1:1 next_pid=21 next_
↪prio=120
    kworker/1:1   21 [001]   6171.470082: sched_switch: prev_comm=kworker/1:1 prev_
↪pid=21 prev_prio=120 prev_state=S ==> next_comm=perf next_pid=1383 next_prio=120
    perf  1383 [001]   6171.480035: sched_wakeup: comm=kworker/1:1 pid=21_
↪prio=120 success=1 target_cpu=001

```

## Filtraggio

Notare che ci sono molti eventi che non hanno nulla a che fare con ciò che ci interessa, ovvero gli eventi che pianificano l'avvio e la disattivazione di perf o che lo riattivano. Possiamo eliminarli utilizzando l'opzione `--filter`: per ogni evento specificato con `-e`, possiamo aggiungere `--filter` per filtrare gli eventi di traccia che contengono campi con valori specifici:

```

root@crownbay:~# perf record -a -e sched:sched_switch --filter 'next_comm != perf &
↪& prev_comm != perf' -e sched:sched_wakeup --filter 'comm != perf'
^C[ perf record: Woken up 38 times to write data ]
[ perf record: Captured and wrote 9.688 MB perf.data (~423279 samples) ]

root@crownbay:~# perf script

    swapper      0 [000]   7932.162180: sched_switch: prev_comm=swapper/0 prev_
↪pid=0 prev_prio=120 prev_state=R ==> next_comm=kworker/0:3 next_pid=1209 next_
↪prio=120
    kworker/0:3  1209 [000]   7932.162236: sched_switch: prev_comm=kworker/0:3 prev_
↪pid=1209 prev_prio=120 prev_state=S ==> next_comm=swapper/0 next_pid=0 next_
↪prio=120
    perf  1407 [001]   7932.170048: sched_wakeup: comm=kworker/1:1 pid=21_
↪prio=120 success=1 target_cpu=001
    perf  1407 [001]   7932.180044: sched_wakeup: comm=kworker/1:1 pid=21_
↪prio=120 success=1 target_cpu=001
    perf  1407 [001]   7932.190038: sched_wakeup: comm=kworker/1:1 pid=21_

```

(continues on next page)

(continua dalla pagina precedente)

```

↪prio=120 success=1 target_cpu=001
    perf  1407 [001]  7932.200044: sched_wakeup: comm=kworker/1:1 pid=21
↪prio=120 success=1 target_cpu=001
    perf  1407 [001]  7932.210044: sched_wakeup: comm=kworker/1:1 pid=21
↪prio=120 success=1 target_cpu=001
    perf  1407 [001]  7932.220044: sched_wakeup: comm=kworker/1:1 pid=21
↪prio=120 success=1 target_cpu=001
    swapper      0 [001]  7932.230111: sched_wakeup: comm=kworker/1:1 pid=21
↪prio=120 success=1 target_cpu=001
    swapper      0 [001]  7932.230146: sched_switch: prev_comm=swapper/1 prev_
↪pid=0 prev_prio=120 prev_state=R ==> next_comm=kworker/1:1 next_pid=21 next_
↪prio=120
    kworker/1:1    21 [001]  7932.230205: sched_switch: prev_comm=kworker/1:1 prev_
↪pid=21 prev_prio=120 prev_state=S ==> next_comm=swapper/1 next_pid=0 next_
↪prio=120
    swapper      0 [000]  7932.326109: sched_wakeup: comm=kworker/0:3 pid=1209
↪prio=120 success=1 target_cpu=000
    swapper      0 [000]  7932.326171: sched_switch: prev_comm=swapper/0 prev_
↪pid=0 prev_prio=120 prev_state=R ==> next_comm=kworker/0:3 next_pid=1209 next_
↪prio=120
    kworker/0:3   1209 [000]  7932.326214: sched_switch: prev_comm=kworker/0:3 prev_
↪pid=1209 prev_prio=120 prev_state=S ==> next_comm=swapper/0 next_pid=0 next_
↪prio=120

```

In questo caso, abbiamo filtrato tutti gli eventi che contengono perf nei campi comm, comm\_prev o comm\_next. Notare che sono ancora registrati eventi per perf, ma notate che questi eventi non hanno il valore perf per i campi filtrati. Per filtrare completamente tutto ciò che riguarda perf sarà necessario un lavoro più complesso, ma ai fini di questa dimostrazione sull'utilizzo dei filtri, è sufficiente.

#### Unire il Tutto

Si tratta esattamente dello stesso set di filtri per eventi definito dal sottosistema di eventi di tracciamento. Per ulteriori informazioni su questi filtri, consultare la sezione ftrace / trace-cmd / KernelShark.

#### Unire il Tutto

Questi filtri sono implementati da uno pseudo-interprete dedicato nel kernel e rappresentano una parte integrante e indispensabile dell'architettura di perf per quanto riguarda il tracciamento. I filtri per eventi basati sul kernel forniscono un meccanismo per limitare con precisione il flusso di eventi che appare nello spazio utente, dove ha senso fornire binding a linguaggi di programmazione reali per l'elaborazione successiva del flusso di eventi. Questa architettura consente una partizione intelligente e flessibile dell'elaborazione tra il kernel e lo spazio utente. Si confronti questo approccio con altri strumenti come SystemTap, che esegue tutta l'elaborazione nel kernel e, come tale, richiede un linguaggio specifico definito dal progetto per adattarsi a tale architettura, o LTTng, dove

tutto viene inviato allo spazio utente e, come tale, richiede un meccanismo di trasporto dal kernel allo spazio utente estremamente efficiente per funzionare correttamente. Sebbene perf possa certamente trarre vantaggio, ad esempio, da progressi nella progettazione del trasporto, non ne dipende fondamentalmente. In sostanza, se la propria applicazione di tracciamento delle prestazioni causa overflow del buffer I/O, probabilmente significa che non si sta sfruttando a sufficienza il motore di filtraggio del kernel.

## Utilizzo di Tracepoint Dinamici

perf non è limitato al set fisso di tracepoint statici elencati da `perf list`. Gli utenti possono anche aggiungere i propri tracepoint "dinamici" in qualsiasi punto del kernel. Ad esempio, supponiamo di voler definire un nostro tracepoint su `do_fork()`. Possiamo farlo usando il sottocomando `perf probe` di perf:

```
root@crownbay:~# perf probe do_fork
Added new event:
  probe:do_fork          (on do_fork)

You can now use it in all perf tools, such as:

perf record -e probe:do_fork -aR sleep 1
```

L'aggiunta di un nuovo tracepoint tramite `perf probe` genera un evento con tutti i file e il formato previsti in `/sys/kernel/debug/tracing/events`, proprio come per i tracepoint statici (come discusso più dettagliatamente nella sezione relativa al sottosistema degli eventi di traccia):

```
root@crownbay:/sys/kernel/debug/tracing/events/probe/do_fork# ls -al
drwxr-xr-x  2 root    root          0 Oct 28 11:42 .
drwxr-xr-x  3 root    root          0 Oct 28 11:42 ..
-rw-r--r--  1 root    root          0 Oct 28 11:42 enable
-rw-r--r--  1 root    root          0 Oct 28 11:42 filter
-r--r--r--  1 root    root          0 Oct 28 11:42 format
-r--r--r--  1 root    root          0 Oct 28 11:42 id

root@crownbay:/sys/kernel/debug/tracing/events/probe/do_fork# cat format
name: do_fork
ID: 944
format:
    field:unsigned short common_type;      offset:0;      size:2; signed:0;
    field:unsigned char common_flags;      offset:2;      size:1; signed:0;
    field:unsigned char common_preempt_count;  offset:3;      size:1; ↵
↵signed:0;
    field:int common_pid;                    offset:4;      size:4; signed:1;
    field:int common_padding;                offset:8;      size:4; signed:1;

    field:unsigned long __probe_ip;          offset:12;     size:4; signed:0;
```

(continues on next page)



(continua dalla pagina precedente)

```
print fmt: "(%lx)", REC->__probe_ip
```

Possiamo elencare tutti i tracepoint dinamici attualmente esistenti:

```
root@crownbay:~# perf probe -l
probe:do_fork (on do_fork)
probe:schedule (on schedule)
```

Registriamo a livello di sistema (`sleep 30` è un trucco per registrare a livello di sistema, ma in pratica non fa nulla e poi si riattiva dopo 30 secondi):

```
root@crownbay:~# perf record -g -a -e probe:do_fork sleep 30
[ perf record: Woken up 1 times to write data ]
[ perf record: Captured and wrote 0.087 MB perf.data (~3812 samples) ]
```

Usando `perf script` possiamo vedere ogni evento `do_fork` che si è attivato:

```
root@crownbay:~# perf script

# =====
# captured on: Sun Oct 28 11:55:18 2012
# hostname : crownbay
# os release : 3.4.11-yocto-standard
# perf version : 3.4.11
# arch : i686
# nrcpus online : 2
# nrcpus avail : 2
# cpudesc : Intel(R) Atom(TM) CPU E660 @ 1.30GHz
# cpuid : GenuineIntel,6,38,1
# total memory : 1017184 kB
# cmdline : /usr/bin/perf record -g -a -e probe:do_fork sleep 30
# event : name = probe:do_fork, type = 2, config = 0x3b0, config1 = 0x0, config2 = 0x0,
↳ 0x0, excl_usr = 0, excl_kern
= 0, id = { 5, 6 }
# HEADER_CPU_TOPOLOGY info available, use -I to display
# =====
#
matchbox-deskto 1197 [001] 34211.378318: do_fork: (c1028460)
matchbox-deskto 1295 [001] 34211.380388: do_fork: (c1028460)
pcmanfm 1296 [000] 34211.632350: do_fork: (c1028460)
pcmanfm 1296 [000] 34211.639917: do_fork: (c1028460)
matchbox-deskto 1197 [001] 34217.541603: do_fork: (c1028460)
matchbox-deskto 1299 [001] 34217.543584: do_fork: (c1028460)
```

(continues on next page)

(continua dalla pagina precedente)

```

gthumb 1300 [001] 34217.697451: do_fork: (c1028460)
gthumb 1300 [001] 34219.085734: do_fork: (c1028460)
gthumb 1300 [000] 34219.121351: do_fork: (c1028460)
gthumb 1300 [001] 34219.264551: do_fork: (c1028460)
pcmanfm 1296 [000] 34219.590380: do_fork: (c1028460)
matchbox-deskto 1197 [001] 34224.955965: do_fork: (c1028460)
matchbox-deskto 1306 [001] 34224.957972: do_fork: (c1028460)
matchbox-termin 1307 [000] 34225.038214: do_fork: (c1028460)
matchbox-termin 1307 [001] 34225.044218: do_fork: (c1028460)
matchbox-termin 1307 [000] 34225.046442: do_fork: (c1028460)
matchbox-deskto 1197 [001] 34237.112138: do_fork: (c1028460)
matchbox-deskto 1311 [001] 34237.114106: do_fork: (c1028460)
gaku 1312 [000] 34237.202388: do_fork: (c1028460)

```

E usando `perf report` sullo stesso file, possiamo vedere i grafici delle chiamate dall'avvio di alcuni programmi durante quei 30 secondi:

```

trz@empanada:~/danny-meta-intel-release
File Edit View Search Terminal Help
Events: 19 probe:do_fork
- 42.11% matchbox-deskto [kernel.kallsyms] [k] do_fork
  do_fork
  ptregs_clone
  __libc_fork
  fork_exec_with_pipes
- 21.05% gthumb [kernel.kallsyms] [k] do_fork
  do_fork
  ptregs_clone
  __clone
  0
- 15.79% pcmanfm [kernel.kallsyms] [k] do_fork
  do_fork
  ptregs_clone
  __clone
  0
- 15.79% matchbox-termin [kernel.kallsyms] [k] do_fork
  - do_fork
  - ptregs_clone
    - 66.67% __libc_fork
      50.00% vte_pty_initable_init
      50.00% fork_exec_with_pipes
    - 33.33% __clone
      0
- 5.26% gaku [kernel.kallsyms] [k] do_fork
  do_fork
  ptregs_clone
  __libc_fork
  fork
Press '?' for help on key bindings

```

**i Unire il Tutto**

Il sottosistema degli eventi di traccia gestisce i tracepoint statici e dinamici esattamente allo stesso modo: non c'è alcuna differenza per quanto riguarda l'infrastruttura interessata. Per maggiori dettagli sul sottosistema degli eventi di traccia, consultare la sezione `ftrace`.

**i Unire il Tutto**

I punti di traccia dinamici sono implementati internamente da Kprobes e Uprobes. Kprobes e Uprobes sono utilizzati anche da SystemTap e ne costituiscono l'obiettivo principale.

## Documentazione di perf

Le versioni online delle pagine di manuale per i comandi discussi in questa sezione sono disponibili qui:

- Il `'perf stat' manual page`.
- Il `'perf record' manual page`.
- Il `'perf report' manual page`.
- Il `'perf probe' manual page`.
- Il `'perf script' manual page`.
- Documentazione sull'utilizzo di `'perf script' Python binding`.
- Il livello superiore `perf(1) manual page`.

Normalmente, si dovrebbe essere in grado di aprire le pagine del manuale tramite `perf` stesso, ad esempio `perf help` o `perf help record`.

Per installare le pagine del manuale di `perf` sul sistema target, modificare la configurazione come segue:

```
IMAGE_INSTALL:append = " perf perf-doc"
DISTRO_FEATURES:append = " api-documentation"
```

Le pagine del manuale in formato testo, insieme ad altri file, come una serie di esempi, si trovano anche nella directory `perf` dell'albero del kernel:

```
tools/perf/Documentation
```

Esiste anche un utile tutorial su `perf` sul wiki di `perf` che approfondisce alcuni argomenti in modo più dettagliato rispetto a quanto facciamo qui: [perf Tutorial](#)

### 11.3.2 ftrace

"ftrace" si riferisce letteralmente al "ftrace function tracer" [tracer di funzioni `ftrace`], ma in realtà comprende diversi tracer correlati, insieme all'infrastruttura che tutti utilizzano.

## Configurazione di ftrace

Per questa sezione, daremo per scontato che sia stata già eseguito la configurazione di base descritta nella sezione "*Configurazione Generale*".

ftrace, trace-cmd e KernelShark vengono eseguiti sul sistema target e sono pronti all'uso fin da subito: non è necessaria alcuna configurazione aggiuntiva. Per il resto di questa sezione, si presume che si sia connessi all'host tramite SSH e che si esegua ftrace sul sistema target. KernelShark è un'applicazione con interfaccia grafica e, utilizzando l'opzione `-X a ssh`, è possibile eseguire l'interfaccia grafica di KernelShark sul sistema target e visualizzarla in remoto sull'host, se lo si desidera.

## Utilizzo di base di ftrace

"ftrace" si riferisce essenzialmente a tutto ciò che è incluso nella directory `/tracing` del filesystem `debugfs` montato (Yocto segue la convenzione standard e lo monta in `/sys/kernel/debug`). Tutti i file presenti in `/sys/kernel/debug/tracing` su un sistema Yocto sono:

```
root@sugarbay:/sys/kernel/debug/tracing# ls
README                                kprobe_events                        trace
available_events                     kprobe_profile                      trace_clock
available_filter_functions            options                             trace_marker
available_tracers                     per_cpu                             trace_options
buffer_size_kb                       printk_formats                      trace_pipe
buffer_total_size_kb                 saved_cmdlines                      tracing_cpumask
current_tracer                       set_event                           tracing_enabled
dyn_ftrace_total_info                set_ftrace_filter                  tracing_on
enabled_functions                    set_ftrace_notrace                 tracing_thresh
events                               set_ftrace_pid                     tracing_thresh
free_buffer                          set_graph_function
```

I file sopra elencati hanno diverse funzioni: alcuni sono direttamente correlati ai tracer stessi, altri vengono utilizzati per impostare le opzioni di tracciamento e altri ancora contengono l'output di tracciamento quando un tracer è attivo. Alcune funzioni possono essere intuite dal nome, altre necessitano di una spiegazione; in ogni caso, analizzeremo alcuni dei file qui di seguito, ma per una spiegazione degli altri, si prega di consultare la documentazione di ftrace.

Iniziamo esaminando alcuni dei tracer integrati disponibili.

Il file `available_tracers` elenca l'insieme dei tracer disponibili:

```
root@sugarbay:/sys/kernel/debug/tracing# cat available_tracers
blk function_graph function nop
```

Il file `current_tracer` contiene il tracer attualmente attivo:

```
root@sugarbay:/sys/kernel/debug/tracing# cat current_tracer
nop
```

L'elenco di `current_tracer` sopra riportato mostra che è attivo il tracer `nop`, il che significa che al momento non è attivo alcun tracer.

Scrivendo uno dei tracer disponibili in `current_tracer`, il tracer specificato diventa il tracer corrente:

```
root@sugarbay:/sys/kernel/debug/tracing# echo function > current_tracer
root@sugarbay:/sys/kernel/debug/tracing# cat current_tracer
function
```

Il comando precedente imposta il tracer corrente su `function`. Questo tracer traccia ogni chiamata di funzione nel kernel e la rende disponibile come contenuto del file `trace`. La lettura del file `trace` elenca le chiamate di funzione attualmente memorizzate nel buffer che sono state tracciate dal tracer di funzione:

```
root@sugarbay:/sys/kernel/debug/tracing# cat trace | less

# tracer: function
#
# entries-in-buffer/entries-written: 310629/766471   #P:8
#
#          _-----=> irqs-off
#          / _-----=> need-resched
#          | / _---=> hardirq/softirq
#          || / _--=> preempt-depth
#          ||| /      delay
#
# TASK-PID   CPU#  ||||   TIMESTAMP  FUNCTION
#   /   /       /   /         /
<idle>-0    [004] d..1   470.867169: ktime_get_real <-intel_idle
<idle>-0    [004] d..1   470.867170: getnstimeofday <-ktime_get_real
<idle>-0    [004] d..1   470.867171: ns_to_timeval <-intel_idle
<idle>-0    [004] d..1   470.867171: ns_to_timespec <-ns_to_timeval
<idle>-0    [004] d..1   470.867172: smp_apic_timer_interrupt <-apic_
↪timer_interrupt
<idle>-0    [004] d..1   470.867172: native_apic_mem_write <-smp_apic_
↪timer_interrupt
<idle>-0    [004] d..1   470.867172: irq_enter <-smp_apic_timer_interrupt
<idle>-0    [004] d..1   470.867172: rcu_irq_enter <-irq_enter
<idle>-0    [004] d..1   470.867173: rcu_idle_exit_common.isra.33 <-rcu_
↪irq_enter
<idle>-0    [004] d..1   470.867173: local_bh_disable <-irq_enter
<idle>-0    [004] d..1   470.867173: add_preempt_count <-local_bh_disable
<idle>-0    [004] d.s1   470.867174: tick_check_idle <-irq_enter
<idle>-0    [004] d.s1   470.867174: tick_check_oneshot_broadcast <-tick_
↪check_idle
<idle>-0    [004] d.s1   470.867174: ktime_get <-tick_check_idle
<idle>-0    [004] d.s1   470.867174: tick_nohz_stop_idle <-tick_check_
↪idle
<idle>-0    [004] d.s1   470.867175: update_ts_time_stats <-tick_nohz_
↪stop_idle
```

(continues on next page)

(continua dalla pagina precedente)

```

<idle>-0      [004] d.s1  470.867175: nr_iowait_cpu <-update_ts_time_stats
<idle>-0      [004] d.s1  470.867175: tick_do_update_jiffies64 <-tick_
↪check_idle
<idle>-0      [004] d.s1  470.867175: _raw_spin_lock <-tick_do_update_
↪jiffies64
<idle>-0      [004] d.s1  470.867176: add_preempt_count <-_raw_spin_lock
<idle>-0      [004] d.s2  470.867176: do_timer <-tick_do_update_jiffies64
<idle>-0      [004] d.s2  470.867176: _raw_spin_lock <-do_timer
<idle>-0      [004] d.s2  470.867176: add_preempt_count <-_raw_spin_lock
<idle>-0      [004] d.s3  470.867177: ntp_tick_length <-do_timer
<idle>-0      [004] d.s3  470.867177: _raw_spin_lock_irqsave <-ntp_tick_
↪length
.
.
.
```

Ogni riga della traccia sopra riportata mostra cosa stava accadendo nel kernel su una data CPU, con un livello di dettaglio pari a quello delle chiamate di funzione. Ogni voce mostra la funzione chiamata, seguita dal suo chiamante (dopo la freccia).

Il tracer function fornisce un'idea estremamente dettagliata di cosa stava facendo il kernel nel momento in cui è stata acquisita la traccia ed è un ottimo strumento per comprendere il funzionamento dinamico del codice del kernel.

### Unire il Tutto

Il tracer function `ftrace` è disponibile anche all'interno di `perf`, come tracepoint `ftrace:function`.

Seguire la catena delle chiamate è un po' più complicato del necessario, ma fortunatamente esiste una variante del tracer function che le visualizza esplicitamente, chiamato `tracer function_graph`:

```

root@sugarbay:/sys/kernel/debug/tracing# echo function_graph > current_tracer
root@sugarbay:/sys/kernel/debug/tracing# cat trace | less
```

```
tracer: function_graph
```

| CPU | DURATION | FUNCTION CALLS           |
|-----|----------|--------------------------|
|     |          |                          |
| 7)  | 0.046 us | pick_next_task_fair();   |
| 7)  | 0.043 us | pick_next_task_stop();   |
| 7)  | 0.042 us | pick_next_task_rt();     |
| 7)  | 0.032 us | pick_next_task_fair();   |
| 7)  | 0.030 us | pick_next_task_idle();   |
| 7)  |          | _raw_spin_unlock_irq() { |
| 7)  | 0.033 us | sub_preempt_count();     |

(continues on next page)

(continua dalla pagina precedente)

```

7) 0.258 us | }
7) 0.032 us | sub_preempt_count();
7) + 13.341 us | } /* __schedule */
7) 0.095 us | } /* sub_preempt_count */
7) | schedule() {
7) | __schedule() {
7) 0.060 us | add_preempt_count();
7) 0.044 us | rcu_note_context_switch();
7) | _raw_spin_lock_irq() {
7) 0.033 us | add_preempt_count();
7) 0.247 us | }
7) | idle_balance() {
7) | _raw_spin_unlock() {
7) 0.031 us | sub_preempt_count();
7) 0.246 us | }
7) | update_shares() {
7) 0.030 us | __rcu_read_lock();
7) 0.029 us | __rcu_read_unlock();
7) 0.484 us | }
7) 0.030 us | __rcu_read_lock();
7) | load_balance() {
7) | find_busiest_group() {
7) 0.031 us | idle_cpu();
7) 0.029 us | idle_cpu();
7) 0.035 us | idle_cpu();
7) 0.906 us | }
7) 1.141 us | }
7) 0.022 us | msecs_to_jiffies();
7) | load_balance() {
7) | find_busiest_group() {
7) 0.031 us | idle_cpu();
.
.
.
4) 0.062 us | msecs_to_jiffies();
4) 0.062 us | __rcu_read_unlock();
4) | _raw_spin_lock() {
4) 0.073 us | add_preempt_count();
4) 0.562 us | }
4) + 17.452 us | }
4) 0.108 us | put_prev_task_fair();
4) 0.102 us | pick_next_task_fair();
4) 0.084 us | pick_next_task_stop();

```

(continues on next page)

(continua dalla pagina precedente)

```

4) 0.075 us | pick_next_task_rt();
4) 0.062 us | pick_next_task_fair();
4) 0.066 us | pick_next_task_idle();
-----
4) kworker-74 => <idle>-0
-----

4) | finish_task_switch() {
4) |     _raw_spin_unlock_irq() {
4) 0.100 us |         sub_preempt_count();
4) 0.582 us |     }
4) 1.105 us | }
4) 0.088 us | sub_preempt_count();
4) ! 100.066 us | }
.
.
.
3) | sys_ioctl() {
3) 0.083 us |     fget_light();
3) |     security_file_ioctl() {
3) 0.066 us |         cap_file_ioctl();
3) 0.562 us |     }
3) |     do_vfs_ioctl() {
3) |         drm_ioctl() {
3) 0.075 us |             drm_ut_debug_printk();
3) |             i915_gem_pwrite_ioctl() {
3) |                 i915_mutex_lock_interruptible() {
3) 0.070 us |                     mutex_lock_interruptible();
3) 0.570 us |                 }
3) |                 drm_gem_object_lookup() {
3) |                     _raw_spin_lock() {
3) 0.080 us |                         add_preempt_count();
3) 0.620 us |                     }
3) |                     _raw_spin_unlock() {
3) 0.085 us |                         sub_preempt_count();
3) 0.562 us |                     }
3) 2.149 us |                 }
3) 0.133 us |             i915_gem_object_pin();
3) |             i915_gem_object_set_to_gtt_domain() {
3) 0.065 us |                 i915_gem_object_flush_gpu_write_domain();
3) 0.065 us |                 i915_gem_object_wait_rendering();
3) 0.062 us |                 i915_gem_object_flush_cpu_write_domain();
3) 1.612 us |             }

```

(continues on next page)



(continua dalla pagina precedente)

```

3)          |          i915_gem_object_put_fence() {
3)  0.097 us |          i915_gem_object_flush_fence.constprop.36();
3)  0.645 us |          }
3)  0.070 us |          add_preempt_count();
3)  0.070 us |          sub_preempt_count();
3)  0.073 us |          i915_gem_object_unpin();
3)  0.068 us |          mutex_unlock();
3)  9.924 us |          }
3) + 11.236 us |      }
3) + 11.770 us |  }
3) + 13.784 us |  }
3)          |  sys_ioctl() {

```

Come si vede, la visualizzazione di `function_graph` è molto più facile da seguire. Inoltre, oltre alle chiamate di funzione e alle parentesi graffe associate, vengono visualizzati anche altri eventi, come gli eventi dello scheduler, nel loro contesto. È possibile includere liberamente qualsiasi punto di tracciamento disponibile nel sottosistema degli eventi di tracciamento descritto nella sezione successiva, semplicemente abilitando tali eventi, che appariranno nel contesto della visualizzazione del grafico delle funzioni. Uno strumento davvero potente per comprendere le dinamiche del kernel.

Si notino anche le varie annotazioni presenti sul lato sinistro della visualizzazione. Ad esempio, se il tempo totale impiegato per l'esecuzione di una determinata funzione supera una certa soglia, sul lato sinistro compare un punto esclamativo o un segno più. Per maggiori dettagli su tutti questi campi, consultate la documentazione di `ftrace`.

### Il sottosistema dei 'trace events'

Una directory particolarmente importante all'interno della directory `/sys/kernel/debug/tracing` è la sottodirectory `events`, che contiene la rappresentazione di ogni tracepoint del sistema. Elencando il contenuto della sottodirectory `events`, vediamo principalmente un altro insieme di sottodirectory:

```

root@sugarbay:/sys/kernel/debug/tracing# cd events
root@sugarbay:/sys/kernel/debug/tracing/events# ls -al
drwxr-xr-x 38 root root 0 Nov 14 23:19 .
drwxr-xr-x 5 root root 0 Nov 14 23:19 ..
drwxr-xr-x 19 root root 0 Nov 14 23:19 block
drwxr-xr-x 32 root root 0 Nov 14 23:19 btrfs
drwxr-xr-x 5 root root 0 Nov 14 23:19 drm
-rw-r--r-- 1 root root 0 Nov 14 23:19 enable
drwxr-xr-x 40 root root 0 Nov 14 23:19 ext3
drwxr-xr-x 79 root root 0 Nov 14 23:19 ext4
drwxr-xr-x 14 root root 0 Nov 14 23:19 ftrace
drwxr-xr-x 8 root root 0 Nov 14 23:19 hda
-r--r--r-- 1 root root 0 Nov 14 23:19 header_event
-r--r--r-- 1 root root 0 Nov 14 23:19 header_page
drwxr-xr-x 25 root root 0 Nov 14 23:19 i915

```

(continues on next page)

(continua dalla pagina precedente)

```

drwxr-xr-x  7 root    root          0 Nov 14 23:19 irq
drwxr-xr-x 12 root    root          0 Nov 14 23:19 jbd
drwxr-xr-x 14 root    root          0 Nov 14 23:19 jbd2
drwxr-xr-x 14 root    root          0 Nov 14 23:19 kmem
drwxr-xr-x  7 root    root          0 Nov 14 23:19 module
drwxr-xr-x  3 root    root          0 Nov 14 23:19 napi
drwxr-xr-x  6 root    root          0 Nov 14 23:19 net
drwxr-xr-x  3 root    root          0 Nov 14 23:19 oom
drwxr-xr-x 12 root    root          0 Nov 14 23:19 power
drwxr-xr-x  3 root    root          0 Nov 14 23:19 printk
drwxr-xr-x  8 root    root          0 Nov 14 23:19 random
drwxr-xr-x  4 root    root          0 Nov 14 23:19 raw_syscalls
drwxr-xr-x  3 root    root          0 Nov 14 23:19 rcu
drwxr-xr-x  6 root    root          0 Nov 14 23:19 rpm
drwxr-xr-x 20 root    root          0 Nov 14 23:19 sched
drwxr-xr-x  7 root    root          0 Nov 14 23:19 scsi
drwxr-xr-x  4 root    root          0 Nov 14 23:19 signal
drwxr-xr-x  5 root    root          0 Nov 14 23:19 skb
drwxr-xr-x  4 root    root          0 Nov 14 23:19 sock
drwxr-xr-x 10 root    root          0 Nov 14 23:19 sunrpc
drwxr-xr-x 538 root    root          0 Nov 14 23:19 syscalls
drwxr-xr-x  4 root    root          0 Nov 14 23:19 task
drwxr-xr-x 14 root    root          0 Nov 14 23:19 timer
drwxr-xr-x  3 root    root          0 Nov 14 23:19 udp
drwxr-xr-x 21 root    root          0 Nov 14 23:19 vmscan
drwxr-xr-x  3 root    root          0 Nov 14 23:19 vsyscall
drwxr-xr-x  6 root    root          0 Nov 14 23:19 workqueue
drwxr-xr-x 26 root    root          0 Nov 14 23:19 writeback

```

Ciascuna di queste sottodirectory corrisponde a un "sottosistema" e contiene a sua volta altre sottodirectory, ognuna delle quali corrisponde infine a un tracepoint. Ad esempio, ecco il contenuto del sottosistema `kmem`:

```

root@sugarbay:/sys/kernel/debug/tracing/events# cd kmem
root@sugarbay:/sys/kernel/debug/tracing/events/kmem# ls -al
drwxr-xr-x 14 root    root          0 Nov 14 23:19 .
drwxr-xr-x 38 root    root          0 Nov 14 23:19 ..
-rw-r--r--  1 root    root          0 Nov 14 23:19 enable
-rw-r--r--  1 root    root          0 Nov 14 23:19 filter
drwxr-xr-x  2 root    root          0 Nov 14 23:19 kfree
drwxr-xr-x  2 root    root          0 Nov 14 23:19 kmalloc
drwxr-xr-x  2 root    root          0 Nov 14 23:19 kmalloc_node
drwxr-xr-x  2 root    root          0 Nov 14 23:19 kmem_cache_alloc
drwxr-xr-x  2 root    root          0 Nov 14 23:19 kmem_cache_alloc_node

```

(continues on next page)

(continua dalla pagina precedente)

```
drwxr-xr-x  2 root    root          0 Nov 14 23:19 kmem_cache_free
drwxr-xr-x  2 root    root          0 Nov 14 23:19 mm_page_alloc
drwxr-xr-x  2 root    root          0 Nov 14 23:19 mm_page_alloc_extfrag
drwxr-xr-x  2 root    root          0 Nov 14 23:19 mm_page_alloc_zone_locked
drwxr-xr-x  2 root    root          0 Nov 14 23:19 mm_page_free
drwxr-xr-x  2 root    root          0 Nov 14 23:19 mm_page_free_batched
drwxr-xr-x  2 root    root          0 Nov 14 23:19 mm_page_pcpu_drain
```

Vediamo cosa contiene la sottocartella relativa a uno specifico tracepoint, in questo caso quello per `kmalloc`:

```
root@sugarbay:/sys/kernel/debug/tracing/events/kmem# cd kmalloc
root@sugarbay:/sys/kernel/debug/tracing/events/kmem/kmalloc# ls -al
drwxr-xr-x  2 root    root          0 Nov 14 23:19 .
drwxr-xr-x 14 root    root          0 Nov 14 23:19 ..
-rw-r--r--  1 root    root          0 Nov 14 23:19 enable
-rw-r--r--  1 root    root          0 Nov 14 23:19 filter
-r--r--r--  1 root    root          0 Nov 14 23:19 format
-r--r--r--  1 root    root          0 Nov 14 23:19 id
```

Il file `format` per il tracepoint descrive l'evento in memoria, che viene utilizzato dai vari strumenti di tracing che ora si avvalgono di questi tracepoint per analizzare l'evento e interpretarlo, insieme a un campo `print fmt` che consente a strumenti come `ftrace` di visualizzare l'evento come testo. Il formato dell'evento `kmalloc` è il seguente:

```
root@sugarbay:/sys/kernel/debug/tracing/events/kmem/kmalloc# cat format
name: kmalloc
ID: 313
format:
    field:unsigned short common_type;    offset:0;        size:2; signed:0;
    field:unsigned char common_flags;    offset:2;        size:1; signed:0;
    field:unsigned char common_preempt_count;  offset:3;        size:1; ↵
↪signed:0;
    field:int common_pid;                offset:4;        size:4; signed:1;
    field:int common_padding;            offset:8;        size:4; signed:1;

    field:unsigned long call_site;        offset:16;       size:8; signed:0;
    field:const void * ptr;              offset:24;       size:8; signed:0;
    field:size_t bytes_req;              offset:32;       size:8; signed:0;
    field:size_t bytes_alloc;            offset:40;       size:8; signed:0;
    field:gfp_t gfp_flags;               offset:48;       size:4; signed:0;

print fmt: "call_site=%lx ptr=%p bytes_req=%zu bytes_alloc=%zu gfp_flags=%s", REC->
↪call_site, REC->ptr, REC->bytes_req, REC->bytes_alloc,
(REC->gfp_flags) ? __print_flags(REC->gfp_flags, "|", {(unsigned long)((gfp_
↪t)0x10u) | ((gfp_t)0x40u) | ((gfp_t)0x80u) | ((
```

(continues on next page)

(continua dalla pagina precedente)

```

gfp_t)0x20000u) | (( gfp_t)0x02u) | (( gfp_t)0x08u)) | (( gfp_t)0x4000u) | (( gfp_
↪t)0x10000u) | (( gfp_t)0x1000u) | (( gfp_t)0x200u) | ((
gfp_t)0x400000u)), "GFP_TRANSHUGE"}, {(unsigned long)(( gfp_t)0x10u) | (( gfp_
↪t)0x40u) | (( gfp_t)0x80u) | (( gfp_t)0x20000u) | ((
gfp_t)0x02u) | (( gfp_t)0x08u)), "GFP_HIGHUSER_MOVABLE"}, {(unsigned long)(( gfp_
↪t)0x10u) | (( gfp_t)0x40u) | (( gfp_t)0x80u) | ((
gfp_t)0x20000u) | (( gfp_t)0x02u)), "GFP_HIGHUSER"}, {(unsigned long)(( gfp_
↪t)0x10u) | (( gfp_t)0x40u) | (( gfp_t)0x80u) | ((
gfp_t)0x20000u)), "GFP_USER"}, {(unsigned long)(( gfp_t)0x10u) | (( gfp_t)0x40u)↪
↪| (( gfp_t)0x80u) | (( gfp_t)0x80000u)), GFP_TEMPORARY"},
{(unsigned long)(( gfp_t)0x10u) | (( gfp_t)0x40u) | (( gfp_t)0x80u)), "GFP_KERNEL
↪"}, {(unsigned long)(( gfp_t)0x10u) | (( gfp_t)0x40u)),
"GFP_NOFS"}, {(unsigned long)(( gfp_t)0x20u)), "GFP_ATOMIC"}, {(unsigned long)((↪
↪gfp_t)0x10u)), "GFP_NOIO"}, {(unsigned long)((
gfp_t)0x20u), "GFP_HIGH"}, {(unsigned long)(( gfp_t)0x10u), "GFP_WAIT"},
↪{(unsigned long)(( gfp_t)0x40u), "GFP_IO"}, {(unsigned long)((
gfp_t)0x100u), "GFP_COLD"}, {(unsigned long)(( gfp_t)0x200u), "GFP_NOWARN"},
↪{(unsigned long)(( gfp_t)0x400u), "GFP_REPEAT"}, {(unsigned
long)(( gfp_t)0x800u), "GFP_NOFAIL"}, {(unsigned long)(( gfp_t)0x1000u), "GFP_
↪NORETRY"},      {(unsigned long)(( gfp_t)0x4000u), "GFP_COMP"},
{(unsigned long)(( gfp_t)0x8000u), "GFP_ZERO"}, {(unsigned long)(( gfp_t)0x10000u),
↪ "GFP_NOMEMALLOC"}, {(unsigned long)(( gfp_t)0x20000u),
"GFP_HARDWALL"}, {(unsigned long)(( gfp_t)0x40000u), "GFP_THISNODE"}, {(unsigned↪
↪long)(( gfp_t)0x80000u), "GFP_RECLAIMABLE"}, {(unsigned
long)(( gfp_t)0x08u), "GFP_MOVABLE"}, {(unsigned long)(( gfp_t)0), "GFP_NOTRACK"},
↪{(unsigned long)(( gfp_t)0x400000u), "GFP_NO_KSWAPD"},
{(unsigned long)(( gfp_t)0x800000u), "GFP_OTHER_NODE"} ) : "GFP_NOWAIT"

```

Il file `enable` nella directory del tracepoint è ciò che consente all'utente (o a strumenti come `trace-cmd`) di attivare e disattivare il tracepoint. Quando è abilitato, il tracepoint corrispondente inizierà ad apparire nel file `trace` di frace descritto in precedenza. Ad esempio, questo comando attiva il tracepoint `kmalloc`:

```
root@sugarbay:/sys/kernel/debug/tracing/events/kmem/kmalloc# echo 1 > enable
```

Al momento, non siamo interessati al tracer di funzioni o ad altri tracer eventualmente attivi, quindi lo disattiviamo prima. Tuttavia, anche in questo caso, dobbiamo comunque riattivare il tracing per visualizzare gli eventi nel buffer di output:

```
root@sugarbay:/sys/kernel/debug/tracing# echo nop > current_tracer
root@sugarbay:/sys/kernel/debug/tracing# echo 1 > tracing_on
```

Ora, se esaminiamo il file `trace`, non vediamo altro che gli eventi `kmalloc` che abbiamo appena attivato:

```

root@sugarbay:/sys/kernel/debug/tracing# cat trace | less
# tracer: nop
#
# entries-in-buffer/entries-written: 1897/1897   #P:8
#
#           _-----=> irqs-off
#           / _-----=> need-resched
#           | / _---=> hardirq/softirq
#           || / _--=> preempt-depth
#           ||| /      delay
#
#          TASK-PID   CPU#  ||||   TIMESTAMP  FUNCTION
#          | |       |   ||||   |          |
dropbear-1465  [000]  ...1 18154.620753: kmalloc: call_site=ffffffff816650d4_
↳ptr=ffff8800729c3000 bytes_req=2048 bytes_alloc=2048 gfp_flags=GFP_KERNEL
<idle>-0      [000]  ..s3 18154.621640: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d555800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
<idle>-0      [000]  ..s3 18154.621656: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d555800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
matchbox-termin-1361 [001]  ...1 18154.755472: kmalloc: call_site=ffffffff81614050_
↳ptr=ffff88006d5f0e00 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_KERNEL|GFP_
↳REPEAT
Xorg-1264     [002]  ...1 18154.755581: kmalloc: call_site=ffffffff8141abe8_
↳ptr=ffff8800734f4cc0 bytes_req=168 bytes_alloc=192 gfp_flags=GFP_KERNEL|GFP_
↳NOWARN|GFP_NORETRY
Xorg-1264     [002]  ...1 18154.755583: kmalloc: call_site=ffffffff814192a3_
↳ptr=ffff88001f822520 bytes_req=24 bytes_alloc=32 gfp_flags=GFP_KERNEL|GFP_ZERO
Xorg-1264     [002]  ...1 18154.755589: kmalloc: call_site=ffffffff81419edb_
↳ptr=ffff8800721a2f00 bytes_req=64 bytes_alloc=64 gfp_flags=GFP_KERNEL|GFP_ZERO
matchbox-termin-1361 [001]  ...1 18155.354594: kmalloc: call_site=ffffffff81614050_
↳ptr=ffff88006db35400 bytes_req=576 bytes_alloc=1024 gfp_flags=GFP_KERNEL|GFP_
↳REPEAT
Xorg-1264     [002]  ...1 18155.354703: kmalloc: call_site=ffffffff8141abe8_
↳ptr=ffff8800734f4cc0 bytes_req=168 bytes_alloc=192 gfp_flags=GFP_KERNEL|GFP_
↳NOWARN|GFP_NORETRY
Xorg-1264     [002]  ...1 18155.354705: kmalloc: call_site=ffffffff814192a3_
↳ptr=ffff88001f822520 bytes_req=24 bytes_alloc=32 gfp_flags=GFP_KERNEL|GFP_ZERO
Xorg-1264     [002]  ...1 18155.354711: kmalloc: call_site=ffffffff81419edb_
↳ptr=ffff8800721a2f00 bytes_req=64 bytes_alloc=64 gfp_flags=GFP_KERNEL|GFP_ZERO
<idle>-0      [000]  ..s3 18155.673319: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d555800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
dropbear-1465  [000]  ...1 18155.673525: kmalloc: call_site=ffffffff816650d4_
↳ptr=ffff8800729c3000 bytes_req=2048 bytes_alloc=2048 gfp_flags=GFP_KERNEL
<idle>-0      [000]  ..s3 18155.674821: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d554800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC

```

(continues on next page)

(continua dalla pagina precedente)

```

<idle>-0      [000] ..s3 18155.793014: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d554800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
dropbear-1465  [000] ...1 18155.793219: kmalloc: call_site=ffffffff816650d4_
↳ptr=ffff8800729c3000 bytes_req=2048 bytes_alloc=2048 gfp_flags=GFP_KERNEL
<idle>-0      [000] ..s3 18155.794147: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d555800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
<idle>-0      [000] ..s3 18155.936705: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d555800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
dropbear-1465  [000] ...1 18155.936910: kmalloc: call_site=ffffffff816650d4_
↳ptr=ffff8800729c3000 bytes_req=2048 bytes_alloc=2048 gfp_flags=GFP_KERNEL
<idle>-0      [000] ..s3 18155.937869: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d554800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
matchbox-termin-1361 [001] ...1 18155.953667: kmalloc: call_site=ffffffff81614050_
↳ptr=ffff88006d5f2000 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_KERNEL|GFP_
↳REPEAT
Xorg-1264      [002] ...1 18155.953775: kmalloc: call_site=ffffffff8141abe8_
↳ptr=ffff8800734f4cc0 bytes_req=168 bytes_alloc=192 gfp_flags=GFP_KERNEL|GFP_
↳NOWARN|GFP_NORETRY
Xorg-1264      [002] ...1 18155.953777: kmalloc: call_site=ffffffff814192a3_
↳ptr=ffff88001f822520 bytes_req=24 bytes_alloc=32 gfp_flags=GFP_KERNEL|GFP_ZERO
Xorg-1264      [002] ...1 18155.953783: kmalloc: call_site=ffffffff81419edb_
↳ptr=ffff8800721a2f00 bytes_req=64 bytes_alloc=64 gfp_flags=GFP_KERNEL|GFP_ZERO
<idle>-0      [000] ..s3 18156.176053: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d554800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
dropbear-1465  [000] ...1 18156.176257: kmalloc: call_site=ffffffff816650d4_
↳ptr=ffff8800729c3000 bytes_req=2048 bytes_alloc=2048 gfp_flags=GFP_KERNEL
<idle>-0      [000] ..s3 18156.177717: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d555800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
<idle>-0      [000] ..s3 18156.399229: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d555800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
dropbear-1465  [000] ...1 18156.399434: kmalloc: call_site=ffffffff816650d4_
↳ptr=ffff8800729c3000 bytes_req=2048 bytes_alloc=2048 gfp_flags=GFP_KERNEL
↳bytes_alloc=2048 gfp_flags=GFP_KERNEL
<idle>-0      [000] ..s3 18156.400660: kmalloc: call_site=ffffffff81619b36_
↳ptr=ffff88006d554800 bytes_req=512 bytes_alloc=512 gfp_flags=GFP_ATOMIC
matchbox-termin-1361 [001] ...1 18156.552800: kmalloc: call_site=ffffffff81614050_
↳ptr=ffff88006db34800 bytes_req=576 bytes_alloc=1024 gfp_flags=GFP_KERNEL|GFP_
↳REPEAT

```

Per disabilitare nuovamente l'evento `kmalloc`, dobbiamo inviare 0 al file `enable`:

```
root@sugarbay:/sys/kernel/debug/tracing/events/kmem/kmalloc# echo 0 > enable
```

È possibile abilitare un numero qualsiasi di eventi o sottosistemi completi (utilizzando il file `enable` nella directory

del sottosistema) e ottenere un'idea estremamente dettagliata di ciò che accade nel sistema abilitando tutti i tracepoint appropriati.

Diversi strumenti descritti in questa guida svolgono proprio questa funzione, tra cui `trace-cmd` e `KernelShark`, che verranno presentati nella sezione successiva.

#### Unire il Tutto

Questi punti di tracciamento e la loro rappresentazione sono utilizzati non solo da `ftrace`, ma anche da molti altri strumenti trattati in questo documento e costituiscono un punto di integrazione centrale per i vari tracer disponibili in Linux. Sono parte integrante della strumentazione per i seguenti strumenti: `perf`, `LTTng`, `ftrace`, `blktrace` e `SystemTap`.

#### Unire il Tutto

Alla fine, tutti i tracer specifici attualmente disponibili in `/sys/kernel/debug/tracing` verranno rimossi e sostituiti con tracer equivalenti basati sul sottosistema degli "trace events" [eventi di tracciamento].

### trace-cmd / KernelShark

`trace-cmd` è essenzialmente un'interfaccia "wrapper" da riga di comando estesa che nasconde i dettagli di tutti i singoli file in `/sys/kernel/debug/tracing`, consentendo agli utenti di specificare eventi specifici all'interno della sotto-cartella `/sys/kernel/debug/tracing/events/` e di raccogliere tracce evitando di dover gestire direttamente tali dettagli.

Come ulteriore livello di controllo, `KernelShark` fornisce un'interfaccia grafica che consente agli utenti di avviare e interrompere le tracce e specificare set di eventi tramite un'interfaccia intuitiva, e di visualizzare l'output sia come eventi di traccia che come visualizzazione grafica per CPU. Utilizza direttamente `trace-cmd` come strumento interno per realizzare tutto ciò (e, come vedremo, visualizza anche il comando `trace-cmd` che utilizza).


Per avviare una traccia con `KernelShark`, si avvia prima questo tool:

```
root@sugarbay:~# kernelshark
```

Quindi si apre la finestra di dialogo `Capture` selezionandola dal menu di `KernelShark`:

```
Capture | Record
```

Si aprirà la seguente finestra di dialogo, che consente di scegliere uno o più eventi (o anche interi sottosistemi) da tracciare:




Notare che si tratta esattamente degli stessi set di eventi descritti nella precedente sezione relativa ai sottosistemi di tracciamento, ed è proprio da qui che `trace-cmd` li preleva per KernelShark.

Nella schermata precedente, abbiamo deciso di esplorare il sottosistema grafico e quindi abbiamo scelto di tracciare tutti i tracepoints contenuti nei sottosistemi `i915` e `drm`.


Dopo aver fatto ciò, possiamo avviare e interrompere la traccia utilizzando i pulsanti `Run` e `Stop` nell'angolo in basso a destra della finestra di dialogo (lo stesso pulsante si trasformerà in 'Stop' dopo l'avvio della traccia):





Notare che il riquadro di destra mostra l'esatta riga di comando `trace-cmd` utilizzata per eseguire la traccia, insieme ai risultati dell'esecuzione di `trace-cmd`.

Una volta premuto il pulsante `Stop`, la visualizzazione grafica si riempie magicamente con una rappresentazione a colori per CPU dei dati di traccia, insieme all'elenco dettagliato degli eventi sottostante:



Ecco un altro esempio, questa volta una visualizzazione risultante dalla traccia di all events:



Il tool è abbastanza intuitivo, ma per informazioni più dettagliate su come navigare tra i dati, consultate il [sito web di KernelShark](#).

## Documentazione di ftrace

La documentazione di ftrace si trova nella directory Documentation del kernel:

```
Documentation/trace/ftrace.txt
```

Anche la documentazione del sottosistema di tracciamento degli eventi si trova nella directory Documentation del kernel:

```
Documentation/trace/events.txt
```

Una serie di articoli sull'utilizzo di ftrace e trace-cmd è disponibile su LWN:

- [Debug del kernel con ftrace - parte 1](#)
- [Debug del kernel con ftrace - parte 2](#)
- [Segreti del tracer di funzioni ftrace](#)
- [trace-cmd: Un'interfaccia per ftrace](#)

Consultare anche la documentazione di [KernelShark](#) per ulteriori dettagli sull'utilizzo.

Un file README divertente ma utile (una mini-guida al tracing) si trova in `/sys/kernel/debug/tracing/README`.

### 11.3.3 SystemTap

SystemTap è uno strumento di tracing e profiling a livello di sistema basato su script.

Gli script di SystemTap sono programmi simili al C che vengono eseguiti nel kernel per raccogliere/stampare/aggregare dati estratti dal contesto in cui vengono chiamati.

Ad esempio, questa sonda del [tutorial di SystemTap](#) stampa una riga ogni volta che un processo sul sistema esegue `open()` su un file. Per ogni riga, stampa il nome eseguibile del programma che ha aperto il file, insieme al suo PID, e il nome del file aperto (o che ha tentato di aprire), che estrae dalla stringa degli argomenti (`argstr`) della chiamata di sistema `open`.

```
probe syscall.open
{
    printf ("%s(%d) open (%s)\n", execname(), pid(), argstr)
}

probe timer.ms(4000) # after 4 seconds
{
    exit ()
}
```

Normalmente, per eseguire questa sonda [probe], è sufficiente installare SystemTap sul sistema che si desidera analizzare ed eseguire direttamente la sonda su tale sistema, ad esempio, supponendo che il nome del file contenente il testo sopra riportato sia `trace_open.stp`:

```
# stap trace_open.stp
```

Ciò che SystemTap fa internamente per eseguire questo probe [sonda] è: 1) analizzare e convertire la sonda in un form equivalente in linguaggio "C", 2) compilare il form "C" in un modulo del kernel, 3) inserire il modulo nel kernel, attivandolo, e 4) raccogliere i dati generati dalla sonda e visualizzarli all'utente.

Per eseguire i passaggi 1 e 2, il programma `stap` necessita dell'accesso al sistema di compilazione del kernel che ha prodotto il kernel in esecuzione sul sistema sottoposto a sonda [probe]. Nel caso di un tipico sistema embedded (il "target"), il sistema di build del kernel purtroppo non fa in genere parte dell'immagine in esecuzione sul target. Normalmente è disponibile sul sistema "host" che ha prodotto l'immagine target; in questi casi, i passaggi 1 e 2 vengono eseguiti sul sistema host, mentre i passaggi 3 e 4 vengono eseguiti sul sistema target, utilizzando solo il runtime di SystemTap.

Il supporto SystemTap in Yocto presuppone che sul sistema target vengano eseguiti solo i passaggi 3 e 4; è possibile eseguire tutte le operazioni sul sistema target, ma questa sezione considera solo il tipico caso d'uso embedded.

Pertanto, per eseguire uno script SystemTap sul sistema target, è necessario procedere come segue: 1) sul sistema host, compilare la sonda in un modulo del kernel compatibile con il sistema target; 2) copiare il modulo sul sistema target; 3) inserire il modulo nel kernel del sistema target, abilitandolo; e 4) raccogliere i dati generati dalla sonda e visualizzarli all'utente.

## Configurazione di SystemTap

Ci sono molti passaggi e dettagli da considerare, ma fortunatamente Yocto include uno script chiamato `crosstap` che si occupa di questi dettagli, permettendoti di eseguire uno script SystemTap sul sistema remoto, con argomenti se necessario.

Per fare ciò da un host remoto, tuttavia, è necessario avere accesso alla build dell'immagine avviata. Lo script `crosstap` fornisce i dettagli su come fare se lo si esegue sull'host senza aver prima effettuato una build:

```
$ crosstap root@192.168.1.88 trace_open.stp

Error: No target kernel build found.
Did you forget to create a local build of your image?
```

'crosstap' richiede una build SDK locale del sistema target (o una build che includa 'tools-profile') per compilare i moduli del kernel in grado di analizzare il sistema target.

In pratica, ciò significa che si deve fare quanto segue:

- Se si sta utilizzando un'immagine precompilata, scaricare i file tarball della release e/o del BSP utilizzati per creare l'immagine.
- Se si sta lavorando da sorgenti Git, clonare semplicemente i layer di metadati e BSP necessari per creare l'immagine che si avvierà.
- Assicurarsi di essere configurato correttamente per creare una nuova immagine (consultare il file README del BSP e/o la documentazione di base ampiamente disponibile che illustra come creare immagini).
- Crea una versione `-sdk` dell'immagine, ad esempio:

```
$ bitbake core-image-sato-sdk
```

- Oppure si crea un'immagine senza SDK ma si include gli strumenti di profilazione (aggiungere `tools-profile` alla variabile `EXTRA_IMAGE_FEATURES`):

```
$ bitbake core-image-sato
```

Una volta creata l'immagine sul sistema host, si è pronti per avviarla (o l'equivalente immagine precompilata) e utilizzare `crosstap` per analizzarla (prima si deve caricare l'ambiente come di consueto):

```
$ source oe-init-build-env
$ cd ~/my/systemtap/scripts
$ crosstap root@192.168.1.xxx myscript.stp
```

### Nota

SystemTap, che utilizza `crosstap`, presuppone che si possa stabilire una connessione SSH al target remoto. Per i dettagli sulla verifica delle connessioni SSH, consultare la pagina wiki di `crosstap`. Inoltre, la possibilità di connettersi tramite SSH al sistema target non è abilitata di default nelle immagini `*-minimal`.

Pertanto, è necessario creare un'immagine SDK o un'immagine con `tools-profile` come descritto nella sezione "*Configurazione Generale*" di questo manuale e avviare l'immagine di destinazione risultante.

#### Nota

Se si ha una *Build Directory* contenente più macchine, si deve selezionare la *MACHINE* a cui ci si sta connettendo e il kernel nella *Build Directory* di quella macchina deve corrispondere esattamente al kernel del sistema avviato, altrimenti si riceverà il messaggio `crosstap` di cui sopra quando si tenta di eseguire uno script.

## Esecuzione di uno Script su un Target

Una volta completata questa operazione, si dovrebbe essere in grado di eseguire uno script SystemTap sul target:

```
$ cd /path/to/yocto
$ source oe-init-build-env

### Shell environment set up for builds. ###

You can now run 'bitbake <target>'

Common targets are:
    core-image-minimal
    core-image-sato
    meta-toolchain
    meta-ide-support

You can also run generated QEMU images with a command like 'runqemu qemu86-64'
```

Dopodiché, ci si può spostare nella directory contenente gli script utilizzando il comando `cd` e usare `crosstap` per eseguire lo script:

```
$ cd /path/to/my/systemtap/script
$ crosstap root@192.168.7.2 trace_open.stp
```

Se si riscontra un errore di connessione al target, ad esempio:

```
$ crosstap root@192.168.7.2 trace_open.stp
error establishing ssh connection on remote 'root@192.168.7.2'
```

Provare a connettersi al target tramite SSH e verificare cosa succede:

```
$ ssh root@192.168.7.2
```

I problemi di connessione sono spesso dovuti all'inserimento di un indirizzo IP errato o a un `host key verification error`.

Se tutto ha funzionato come previsto, si dovrebbe visualizzare qualcosa di simile a questo (inserire la password quando richiesto o premere Invio se è configurato per non richiedere password):

```
$ crosstap root@192.168.7.2 trace_open.stp
root@192.168.7.2's password:
matchbox-termin(1036) open ("/tmp/vte3FS2LW", O_RDWR|O_CREAT|O_EXCL|O_LARGEFILE, 0600)
matchbox-termin(1036) open ("/tmp/vteJMC7LW", O_RDWR|O_CREAT|O_EXCL|O_LARGEFILE, 0600)
```

## Documentazione di SystemTap

Il riferimento al linguaggio SystemTap è disponibile qui: [Riferimento al Linguaggio SystemTap](#)

I link ad altri documenti, tutorial ed esempi di SystemTap sono disponibili qui: [pagina della documentazione di SystemTap](#)

### 11.3.4 Sysprof

Sysprof è un profiler di sistema facile da usare, composto da un'unica finestra con tre riquadri e alcuni pulsanti che consentono di avviare, arrestare e visualizzare il profilo da un'unica posizione.

#### Configurazione di Sysprof


Per questa sezione, daremo per scontato che sia stata già eseguito la configurazione di base descritta nella sezione "*Configurazione Generale*".

Sysprof è un'applicazione con interfaccia grafica (GUI) che viene eseguita sul sistema target. Per il resto di questo documento, si presume che si sia connessi all'host tramite SSH e che si esegua Sysprof sul sistema target (è possibile utilizzare l'opzione `-x` per connettersi tramite `ssh` e far sì che l'interfaccia grafica di Sysprof venga eseguita sul sistema di destinazione, ma visualizzata in remoto sull'host, se lo si desidera).

#### Utilizzo di Base di Sysprof


Per iniziare la profilazione del sistema, è sufficiente premere il pulsante `Start`. Per interrompere la profilazione e visualizzare i dati di profilazione in un unico passaggio, premere il pulsante `Profile`.

Dopo aver premuto il pulsante `profile`, i tre riquadri si riempiranno con i dati di profilazione:



Il riquadro di sinistra mostra un elenco di funzioni e processi. Selezionandone uno, la funzione corrispondente si espande nel riquadro di destra, mostrando tutti i processi che la chiamano. Si noti che questa visualizzazione orientata al chiamante è essenzialmente l'inverso della visualizzazione predefinita della catena di chiamate di perf, orientata al chiamato.

Nella schermata sopra, ci concentriamo su `__copy_to_user_ll()` e, osservando la catena di chiamate, possiamo vedere che uno dei chiamanti di `__copy_to_user_ll` è `sys_read()` e il percorso completo delle chiamate tra di essi. Si noti che si tratta essenzialmente di una parte delle stesse informazioni che abbiamo visto nella visualizzazione di perf mostrata nella sezione perf di questa pagina.



Analogamente, l'immagine sopra riportata è un'istantanea della visualizzazione di Sysprof di una catena di chiamate `copy-from-user`.



Infine, osservando il terzo riquadro di Sysprof in basso a sinistra, possiamo vedere un elenco di tutti i chiamanti di una particolare funzione selezionata nel riquadro in alto a sinistra. In questo caso, il riquadro inferiore mostra tutti i chiamanti di `__mark_inode_dirty`:

| Functions                      | Self   | Total  |
|--------------------------------|--------|--------|
| sock_aio_read                  | 0.41 % | 9.99 % |
| [sysprof]                      | 0.00 % | 9.49 % |
| inet_recvmsg                   | 0.31 % | 9.13 % |
| generic_file_buffered_write    | 0.08 % | 9.13 % |
| tcp_recvmsg                    | 1.26 % | 8.46 % |
| _raw_spin_unlock_irq           | 7.07 % | 7.46 % |
| poll_schedule_timeout          | 0.15 % | 7.20 % |
| schedule_hrtimeout_range       | 0.08 % | 7.05 % |
| schedule_hrtimeout_range_clock | 0.23 % | 6.92 % |
| __schedule                     | 0.33 % | 6.04 % |
| schedule                       | 0.10 % | 5.63 % |
| kthread                        | 0.00 % | 5.37 % |
| kernel_thread_helper           | 0.00 % | 5.37 % |
| finish_task_switch             | 0.10 % | 5.27 % |
| __mark_inode_dirty             | 0.08 % | 4.40 % |
| ext4_da_write_end              | 0.39 % | 4.32 % |

| Callers                      | Self   | Total  |
|------------------------------|--------|--------|
| generic_write_end            | 0.00 % | 2.88 % |
| file_update_time             | 0.03 % | 1.44 % |
| ext4_da_update_reserve_space | 0.00 % | 0.03 % |
| __generic_file_aio_write     | 0.03 % | 0.03 % |
| ext4_da_write_end            | 0.03 % | 0.03 % |

Facendo doppio clic su una di queste funzioni, il focus si sposterà sulla funzione selezionata, e così via.

#### Unire il Tutto

Se si apprezza la visualizzazione di Sysprof caller-oriented, si potrebbe essere in grado di ottenere un risultato simile anche con altri strumenti. Ad esempio, `perf report` ha l'opzione `-g (--call-graph)` con cui si può sperimentare; una delle opzioni è `caller` per una visualizzazione del grafico delle chiamate basata sui chiamanti invertita.

## Documentazione di Sysprof

Non sembra esserci alcuna documentazione per Sysprof, ma forse è perché è piuttosto intuitivo. Il sito web di Sysprof, tuttavia, è questo: [Sysprof, System-wide Performance Profiler for Linux](#)

### 11.3.5 LTTng (Linux Trace Toolkit, nuova generazione)

#### Configurazione di LTTng

Per questa sezione, daremo per scontato che sia stata già eseguito la configurazione di base descritta nella sezione "[Configurazione Generale](#)". LTTng viene eseguito sul sistema target connettendosi ad esso tramite SSH.

#### Raccolta e Visualizzazione delle Tracce

Dopo aver applicato i commit sopra indicati e aver creato e avviato l'immagine (è necessario creare l'immagine `core-image-sato-sdk` o utilizzare uno degli altri metodi descritti nella sezione "[Configurazione Generale](#)"), si è pronti per iniziare il tracing.

## Raccolta e visualizzazione di una traccia sul target (all'interno di una shell)

Innanzitutto, dall'host, ci si connette al target tramite SSH:

```
$ ssh -l root 192.168.1.47
The authenticity of host '192.168.1.47 (192.168.1.47)' can't be established.
RSA key fingerprint is 23:bd:c8:b1:a8:71:52:00:ee:00:4f:64:9e:10:b9:7e.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.1.47' (RSA) to the list of known hosts.
root@192.168.1.47's password:
```

Una volta sul target, seguire questi passaggi per creare una traccia:

```
root@crownbay:~# lttng create
Spawning a session daemon
Session auto-20121015-232120 created.
Traces will be written in /home/root/lttng-traces/auto-20121015-232120
```

Abilitare gli eventi da tracciare (in questo caso tutti gli eventi del kernel):

```
root@crownbay:~# lttng enable-event --kernel --all
All kernel events are enabled in channel channel0
```

Avviare la traccia:

```
root@crownbay:~# lttng start
Tracing started for session auto-20121015-232120
```

Quindi, si interrompe la traccia dopo un po' di tempo o dopo aver eseguito un particolare carico di lavoro che si desidera tracciare:

```
root@crownbay:~# lttng stop
Tracing stopped for session auto-20121015-232120
```

Ora si può visualizzare la traccia in formato testuale sul target:

```
root@crownbay:~# lttng view
[23:21:56.989270399] (+?.????????) sys_geteuid: { 1 }, { }
[23:21:56.989278081] (+0.000007682) exit_syscall: { 1 }, { ret = 0 }
[23:21:56.989286043] (+0.000007962) sys_pipe: { 1 }, { fildes = 0xB77B9E8C }
[23:21:56.989321802] (+0.000035759) exit_syscall: { 1 }, { ret = 0 }
[23:21:56.989329345] (+0.000007543) sys_mmap_pgoff: { 1 }, { addr = 0x0, len =
↪10485760, prot = 3, flags = 131362, fd = 4294967295, pgoff = 0 }
[23:21:56.989351694] (+0.000022349) exit_syscall: { 1 }, { ret = -1247805440 }
[23:21:56.989432989] (+0.000081295) sys_clone: { 1 }, { clone_flags = 0x411, newsp_
↪= 0xB5EFFFFE4, parent_tid = 0xFFFFFFFF, child_tid = 0x0 }
[23:21:56.989477129] (+0.000044140) sched_stat_runtime: { 1 }, { comm = "lttng-
```

(continues on next page)

(continua dalla pagina precedente)

```

↪consumerd", tid = 1193, runtime = 681660, vruntime = 43367983388 }
[23:21:56.989486697] (+0.000009568) sched_migrate_task: { 1 }, { comm = "lttng-
↪consumerd", tid = 1193, prio = 20, orig_cpu = 1, dest_cpu = 1 }
[23:21:56.989508418] (+0.000021721) hrtimer_init: { 1 }, { hrtimer = 3970832076, ↪
↪clockid = 1, mode = 1 }
[23:21:56.989770462] (+0.000262044) hrtimer_cancel: { 1 }, { hrtimer = 3993865440 }
[23:21:56.989771580] (+0.000001118) hrtimer_cancel: { 0 }, { hrtimer = 3993812192 }
[23:21:56.989776957] (+0.000005377) hrtimer_expire_entry: { 1 }, { hrtimer = ↪
↪3993865440, now = 79815980007057, function = 3238465232 }
[23:21:56.989778145] (+0.000001188) hrtimer_expire_entry: { 0 }, { hrtimer = ↪
↪3993812192, now = 79815980008174, function = 3238465232 }
[23:21:56.989791695] (+0.000013550) softirq_raise: { 1 }, { vec = 1 }
[23:21:56.989795396] (+0.000003701) softirq_raise: { 0 }, { vec = 1 }
[23:21:56.989800635] (+0.000005239) softirq_raise: { 0 }, { vec = 9 }
[23:21:56.989807130] (+0.000006495) sched_stat_runtime: { 1 }, { comm = "lttng-
↪consumerd", tid = 1193, runtime = 330710, vruntime = 43368314098 }
[23:21:56.989809993] (+0.000002863) sched_stat_runtime: { 0 }, { comm = "lttng-
↪sessiond", tid = 1181, runtime = 1015313, vruntime = 36976733240 }
[23:21:56.989818514] (+0.000008521) hrtimer_expire_exit: { 0 }, { hrtimer = ↪
↪3993812192 }
[23:21:56.989819631] (+0.000001117) hrtimer_expire_exit: { 1 }, { hrtimer = ↪
↪3993865440 }
[23:21:56.989821866] (+0.000002235) hrtimer_start: { 0 }, { hrtimer = 3993812192, ↪
↪function = 3238465232, expires = 79815981000000, softexpires = 79815981000000 }
[23:21:56.989822984] (+0.000001118) hrtimer_start: { 1 }, { hrtimer = 3993865440, ↪
↪function = 3238465232, expires = 79815981000000, softexpires = 79815981000000 }
[23:21:56.989832762] (+0.000009778) softirq_entry: { 1 }, { vec = 1 }
[23:21:56.989833879] (+0.000001117) softirq_entry: { 0 }, { vec = 1 }
[23:21:56.989838069] (+0.000004190) timer_cancel: { 1 }, { timer = 3993871956 }
[23:21:56.989839187] (+0.000001118) timer_cancel: { 0 }, { timer = 3993818708 }
[23:21:56.989841492] (+0.000002305) timer_expire_entry: { 1 }, { timer = ↪
↪3993871956, now = 79515980, function = 3238277552 }
[23:21:56.989842819] (+0.000001327) timer_expire_entry: { 0 }, { timer = ↪
↪3993818708, now = 79515980, function = 3238277552 }
[23:21:56.989854831] (+0.000012012) sched_stat_runtime: { 1 }, { comm = "lttng-
↪consumerd", tid = 1193, runtime = 49237, vruntime = 43368363335 }
[23:21:56.989855949] (+0.000001118) sched_stat_runtime: { 0 }, { comm = "lttng-
↪sessiond", tid = 1181, runtime = 45121, vruntime = 36976778361 }
[23:21:56.989861257] (+0.000005308) sched_stat_sleep: { 1 }, { comm = "kworker/1:1
↪", tid = 21, delay = 9451318 }
[23:21:56.989862374] (+0.000001117) sched_stat_sleep: { 0 }, { comm = "kworker/0:0
↪", tid = 4, delay = 9958820 }
[23:21:56.989868241] (+0.000005867) sched_wakeup: { 0 }, { comm = "kworker/0:0", ↪

```

(continues on next page)

(continua dalla pagina precedente)

```

↪tid = 4, prio = 120, success = 1, target_cpu = 0 }
[23:21:56.989869358] (+0.000001117) sched_wakeup: { 1 }, { comm = "kworker/1:1",
↪tid = 21, prio = 120, success = 1, target_cpu = 1 }
[23:21:56.989877460] (+0.000008102) timer_expire_exit: { 1 }, { timer = 3993871956,
↪}
[23:21:56.989878577] (+0.000001117) timer_expire_exit: { 0 }, { timer = 3993818708,
↪}
.
.
.

```

Ora si può terminare la sessione di traccia in modo sicuro (notare che questo non elimina la traccia, che rimane comunque presente in ~/lttng-traces):

```

root@crownbay:~# lttng destroy
Session auto-20121015-232120 destroyed at /home/root

```

Notare che la traccia viene salvata in una directory con lo stesso nome restituito da lttng create, nella directory ~/lttng-traces (notare che l'ora si può modificare specificando un nome personalizzato a lttng create):

```

root@crownbay:~# ls -al ~/lttng-traces
drwxrwx---  3 root    root      1024 Oct 15 23:21 .
drwxr-xr-x  5 root    root      1024 Oct 15 23:57 ..
drwxrwx---  3 root    root      1024 Oct 15 23:21 auto-20121015-232120

```

## Raccolta e visualizzazione di una traccia dello spazio utente sul target (all'interno di una shell)

Per tracciare lo spazio utente con LTTng, è necessario disporre di un programma nello spazio utente opportunamente strumentato [instrumented]. In questo esempio, useremo il programma di test hello generato dalla build lttng-ust.

Il programma di test hello non viene installato sul filesystem di root dalla build lttng-ust, quindi dobbiamo copiarlo manualmente. Per prima cosa, ci si sposta nella directory di build che contiene l'eseguibile hello:

```
$ cd build/tmp/work/core2_32-poky-linux/lttng-ust/2.0.5-r0/git/tests/hello/.libs
```

Copiarlo sulla macchina target:

```
$ scp hello root@192.168.1.20:
```

Ora si ha il programma di test "hello world" di LTTng strumentato sulla macchina target, pronto per essere testato.

Innanzitutto, dall'host, ci si connette al target tramite SSH:

```
$ ssh -l root 192.168.1.47
The authenticity of host '192.168.1.47 (192.168.1.47)' can't be established.
```

(continues on next page)

(continua dalla pagina precedente)

```
RSA key fingerprint is 23:bd:c8:b1:a8:71:52:00:ee:00:4f:64:9e:10:b9:7e.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.1.47' (RSA) to the list of known hosts.
root@192.168.1.47's password:
```

Una volta sul target, seguire questi passaggi per creare una traccia:

```
root@crownbay:~# lttng create
Session auto-20190303-021943 created.
Traces will be written in /home/root/lttng-traces/auto-20190303-021943
```

Abilitare gli eventi da tracciare (in questo caso tutti gli eventi nello spazio utente):

```
root@crownbay:~# lttng enable-event --userspace --all
All UST events are enabled in channel channel0
```

Avviare la traccia:

```
root@crownbay:~# lttng start
Tracing started for session auto-20190303-021943
```

Eeguire il programma "hello world" strumentato [instrumented]:

```
root@crownbay:~# ./hello
Hello, World!
Tracing... done.
```

Quindi, si interrompe la traccia dopo un po' di tempo o dopo aver eseguito un particolare carico di lavoro che si desidera tracciare:

```
root@crownbay:~# lttng stop
Tracing stopped for session auto-20190303-021943
```

Ora si può visualizzare la traccia in formato testuale sul target:

```
root@crownbay:~# lttng view
[02:31:14.906146544] (+?.????????) hello:1424 ust_tests_hello:tpetest: { cpu_id =
↪1 }, { intfield = 0, intfield2 = 0x0, longfield = 0, netintfield = 0,
↪netintfieldhex = 0x0, arrfield1 = [ [0] = 1, [1] = 2, [2] = 3 ], arrfield2 =
↪"test", _seqfield1_length = 4, seqfield1 = [ [0] = 116, [1] = 101, [2] = 115,
↪[3] = 116 ], _seqfield2_length = 4, seqfield2 = "test", stringfield = "test",
↪floatfield = 2222, doublefield = 2, boolfield = 1 }
[02:31:14.906170360] (+0.000023816) hello:1424 ust_tests_hello:tpetest: { cpu_id =
↪1 }, { intfield = 1, intfield2 = 0x1, longfield = 1, netintfield = 1,
↪netintfieldhex = 0x1, arrfield1 = [ [0] = 1, [1] = 2, [2] = 3 ], arrfield2 =
↪"test", _seqfield1_length = 4, seqfield1 = [ [0] = 116, [1] = 101, [2] = 115,
```

(continues on next page)

(continua dalla pagina precedente)

```

↪[3] = 116 ], _seqfield2_length = 4, seqfield2 = "test", stringfield = "test", ↪
↪floatfield = 2222, doublefield = 2, boolfield = 1 }
[02:31:14.906183140] (+0.000012780) hello:1424 ust_tests_hello:tpptest: { cpu_id = ↪
↪1 }, { intfield = 2, intfield2 = 0x2, longfield = 2, netintfield = 2, ↪
↪netintfieldhex = 0x2, arrfield1 = [ [0] = 1, [1] = 2, [2] = 3 ], arrfield2 = ↪
↪"test", _seqfield1_length = 4, seqfield1 = [ [0] = 116, [1] = 101, [2] = 115, ↪
↪[3] = 116 ], _seqfield2_length = 4, seqfield2 = "test", stringfield = "test", ↪
↪floatfield = 2222, doublefield = 2, boolfield = 1 }
[02:31:14.906194385] (+0.000011245) hello:1424 ust_tests_hello:tpptest: { cpu_id = ↪
↪1 }, { intfield = 3, intfield2 = 0x3, longfield = 3, netintfield = 3, ↪
↪netintfieldhex = 0x3, arrfield1 = [ [0] = 1, [1] = 2, [2] = 3 ], arrfield2 = ↪
↪"test", _seqfield1_length = 4, seqfield1 = [ [0] = 116, [1] = 101, [2] = 115, ↪
↪[3] = 116 ], _seqfield2_length = 4, seqfield2 = "test", stringfield = "test", ↪
↪floatfield = 2222, doublefield = 2, boolfield = 1 }
.
.
.

```

Ora si può terminare la sessione di traccia in modo sicuro (notare che questo non elimina la traccia, che rimane comunque presente in `~/ltnng-traces`):

```

root@crownbay:~# ltnng destroy
Session auto-20190303-021943 destroyed at /home/root

```

## Documentazione di LTTng

La documentazione principale di LTTng è disponibile sul sito [LTTng Documentation](#). La documentazione su questo sito è adatta a sviluppatori software di livello intermedio e avanzato che lavorano in un ambiente Linux e sono interessati a un tracing efficiente del software.

Per informazioni generali su LTTng, visitare il sito di [LTTng Project](#). Su questo sito è presente un link "Getting Started" che rimanda a una Guida Rapida di LTTng.

### 11.3.6 blktrace

blktrace è un tool per il tracing e il reporting delle operazioni di I/O del disco di basso livello. blktrace fornisce la parte di tracing; il suo output può essere inviato tramite pipe al programma blkparse, che elabora i dati in un formato leggibile e ne esegue alcune analisi di base:

#### Configurazione di blktrace

Per questa sezione, daremo per scontato che sia stata già eseguito la configurazione di base descritta nella sezione "[Configurazione Generale](#)".

blktrace è un'applicazione che viene eseguita sul target. È possibile eseguire l'intera pipeline blktrace e blkparse sul target, oppure eseguire blktrace in modalità 'listen' sul target e fare in modo che blktrace e blkparse raccolgano e

analizzino i dati sull'host (vedere la sezione "*Utilizzo di blktrace da Remoto*" di seguito). Per il resto di questa sezione, si presume si sia connessi all'host tramite SSH e che si esegua blktrace sul target.

### Utilizzo di base di blktrace

Per registrare una traccia, è sufficiente eseguire il comando `blktrace`, specificando il nome del dispositivo a blocchi su cui si desidera tracciare l'attività:

```
root@crownbay:~# blktrace /dev/sdc
```

In un'altra shell, eseguire il carico di lavoro che si desidera tracciare:

```
root@crownbay:/media/sdc# rm linux-2.6.19.2.tar.bz2; wget https://downloads.
↳yoctoproject.org/mirror/sources/linux-2.6.19.2.tar.bz2; sync
Connecting to downloads.yoctoproject.org (140.211.169.59:80)
linux-2.6.19.2.tar.b 100% \|*****\| 41727k 0:00:00 ETA
```

Premere `Ctrl-C` nella shell di `blktrace` per interrompere la traccia. Verrà visualizzato il numero di eventi registrati, insieme alle dimensioni dei file per ciascuna CPU (`blktrace` registra le tracce nei buffer del kernel di ogni CPU e le salva nello spazio utente affinché `blkparse` le unisca e le ordini in seguito):

```
^C=== sdc ===
CPU 0:          7082 events,      332 KiB data
CPU 1:          1578 events,       74 KiB data
Total:          8660 events (dropped 0),    406 KiB data
```

Esaminando i file salvati su disco, si noteranno più file, uno per ogni CPU, con il nome del dispositivo come prima parte del nome del file:

```
root@crownbay:~# ls -al
drwxr-xr-x  6 root  root    1024 Oct 27 22:39 .
drwxr-sr-x  4 root  root    1024 Oct 26 18:24 ..
-rw-r--r--  1 root  root  339938 Oct 27 22:40 sdc.blktrace.0
-rw-r--r--  1 root  root   75753 Oct 27 22:40 sdc.blktrace.1
```

Per visualizzare gli eventi di traccia, è sufficiente richiamare `blkparse` nella directory contenente i file di traccia, specificando il nome del dispositivo che costituisce la prima parte del nome del file:

```
root@crownbay:~# blkparse sdc

8,32  1      1      0.000000000 1225 Q WS 3417048 + 8 [jbd2/sdc-8]
8,32  1      2      0.000025213 1225 G WS 3417048 + 8 [jbd2/sdc-8]
8,32  1      3      0.000033384 1225 P  N [jbd2/sdc-8]
8,32  1      4      0.000043301 1225 I WS 3417048 + 8 [jbd2/sdc-8]
8,32  1      0      0.000057270   0 m  N cfq1225 insert_request
8,32  1      0      0.000064813   0 m  N cfq1225 add_to_rr
8,32  1      5      0.000076336 1225 U  N [jbd2/sdc-8] 1
```

(continues on next page)

(continua dalla pagina precedente)

|         |   |      |              |      |   |                                     |
|---------|---|------|--------------|------|---|-------------------------------------|
| 8,32    | 1 | 0    | 0.000088559  | 0    | m | N cfq workload slice:150            |
| 8,32    | 1 | 0    | 0.000097359  | 0    | m | N cfq1225 set_active wl_prio:0 wl_  |
| ↪type:1 |   |      |              |      |   |                                     |
| 8,32    | 1 | 0    | 0.000104063  | 0    | m | N cfq1225 Not idling. st->count:1   |
| 8,32    | 1 | 0    | 0.000112584  | 0    | m | N cfq1225 fifo= (null)              |
| 8,32    | 1 | 0    | 0.000118730  | 0    | m | N cfq1225 dispatch_insert           |
| 8,32    | 1 | 0    | 0.000127390  | 0    | m | N cfq1225 dispatched a request      |
| 8,32    | 1 | 0    | 0.000133536  | 0    | m | N cfq1225 activate rq, drv=1        |
| 8,32    | 1 | 6    | 0.000136889  | 1225 | D | WS 3417048 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 7    | 0.000360381  | 1225 | Q | WS 3417056 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 8    | 0.000377422  | 1225 | G | WS 3417056 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 9    | 0.000388876  | 1225 | P | N [jbd2/sdc-8]                      |
| 8,32    | 1 | 10   | 0.000397886  | 1225 | Q | WS 3417064 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 11   | 0.000404800  | 1225 | M | WS 3417064 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 12   | 0.000412343  | 1225 | Q | WS 3417072 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 13   | 0.000416533  | 1225 | M | WS 3417072 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 14   | 0.000422121  | 1225 | Q | WS 3417080 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 15   | 0.000425194  | 1225 | M | WS 3417080 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 16   | 0.000431968  | 1225 | Q | WS 3417088 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 17   | 0.000435251  | 1225 | M | WS 3417088 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 18   | 0.000440279  | 1225 | Q | WS 3417096 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 19   | 0.000443911  | 1225 | M | WS 3417096 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 20   | 0.000450336  | 1225 | Q | WS 3417104 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 21   | 0.000454038  | 1225 | M | WS 3417104 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 22   | 0.000462070  | 1225 | Q | WS 3417112 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 23   | 0.000465422  | 1225 | M | WS 3417112 + 8 [jbd2/sdc-8]         |
| 8,32    | 1 | 24   | 0.000474222  | 1225 | I | WS 3417056 + 64 [jbd2/sdc-8]        |
| 8,32    | 1 | 0    | 0.000483022  | 0    | m | N cfq1225 insert_request            |
| 8,32    | 1 | 25   | 0.000489727  | 1225 | U | N [jbd2/sdc-8] 1                    |
| 8,32    | 1 | 0    | 0.000498457  | 0    | m | N cfq1225 Not idling. st->count:1   |
| 8,32    | 1 | 0    | 0.000503765  | 0    | m | N cfq1225 dispatch_insert           |
| 8,32    | 1 | 0    | 0.000512914  | 0    | m | N cfq1225 dispatched a request      |
| 8,32    | 1 | 0    | 0.000518851  | 0    | m | N cfq1225 activate rq, drv=2        |
| .       |   |      |              |      |   |                                     |
| .       |   |      |              |      |   |                                     |
| .       |   |      |              |      |   |                                     |
| 8,32    | 0 | 0    | 58.515006138 | 0    | m | N cfq3551 complete rqnoidle 1       |
| 8,32    | 0 | 2024 | 58.516603269 | 3    | C | WS 3156992 + 16 [0]                 |
| 8,32    | 0 | 0    | 58.516626736 | 0    | m | N cfq3551 complete rqnoidle 1       |
| 8,32    | 0 | 0    | 58.516634558 | 0    | m | N cfq3551 arm_idle: 8 group_idle: 0 |
| 8,32    | 0 | 0    | 58.516636933 | 0    | m | N cfq schedule dispatch             |
| 8,32    | 1 | 0    | 58.516971613 | 0    | m | N cfq3551 slice expired t=0         |
| 8,32    | 1 | 0    | 58.516982089 | 0    | m | N cfq3551 sl_used=13 disp=6         |

(continues on next page)



(continua dalla pagina precedente)

```

↪charge=13 iops=0 sect=80
8,32  1      0  58.516985511  0 m  N cfq3551 del_from_rr
8,32  1      0  58.516990819  0 m  N cfq3551 put_queue

CPU0 (sdc):
Reads Queued:      0,      0KiB  Writes Queued:      331,  26,
↪284KiB
Read Dispatches:   0,      0KiB  Write Dispatches:   485,  40,
↪484KiB
Reads Requeued:    0              Writes Requeued:      0
Reads Completed:   0,      0KiB  Writes Completed:   511,  41,
↪000KiB
Read Merges:       0,      0KiB  Write Merges:       13,  _
↪160KiB
Read depth:        0              Write depth:         2
IO unplugs:        23             Timer unplugs:       0

CPU1 (sdc):
Reads Queued:      0,      0KiB  Writes Queued:      249,  15,
↪800KiB
Read Dispatches:   0,      0KiB  Write Dispatches:   42,  1,
↪600KiB
Reads Requeued:    0              Writes Requeued:      0
Reads Completed:   0,      0KiB  Writes Completed:   16,  1,
↪084KiB
Read Merges:       0,      0KiB  Write Merges:       40,  _
↪276KiB
Read depth:        0              Write depth:         2
IO unplugs:        30             Timer unplugs:       1

Total (sdc):
Reads Queued:      0,      0KiB  Writes Queued:      580,  42,
↪084KiB
Read Dispatches:   0,      0KiB  Write Dispatches:   527,  42,
↪084KiB
Reads Requeued:    0              Writes Requeued:      0
Reads Completed:   0,      0KiB  Writes Completed:   527,  42,
↪084KiB
Read Merges:       0,      0KiB  Write Merges:       53,  _
↪436KiB
IO unplugs:        53             Timer unplugs:       1

Throughput (R/W): 0KiB/s / 719KiB/s
Events (sdc): 6,592 entries

```

(continues on next page)

(continua dalla pagina precedente)

```
Skips: 0 forward (0 - 0.0%)
Input file sdc.blktrace.0 added
Input file sdc.blktrace.1 added
```

Il report mostra ogni evento rilevato nei dati di blktrace, insieme a un riepilogo del traffico I/O a blocchi complessivo durante l'esecuzione. È possibile consultare la pagina del manuale *blkparse(1)* per conoscere il significato di ciascun campo visualizzato nell'elenco delle tracce.

## Modalità Live

blktrace e blkparse sono stati progettati fin dall'inizio per funzionare insieme in "pipe mode", in cui l'output standard di blktrace può essere inviato direttamente all'input standard di blkparse:

```
root@crownbay:~# blktrace /dev/sdc -o - | blkparse -i -
```

Questo permette di eseguire sessioni di tracciamento di lunga durata senza scrivere nulla su disco e consente all'utente di cercare determinate condizioni nei dati di tracciamento in 'real-time', visualizzando l'output di tracciamento che scorre sullo schermo o passandolo a un altro programma nella pipeline, come grep, che può essere utilizzato per identificare e acquisire le condizioni di interesse.

Esiste in realtà un altro comando blktrace che implementa la pipeline descritta sopra come un singolo comando, quindi l'utente non deve preoccuparsi di digitare la sequenza di comandi precedente:

```
root@crownbay:~# btrace /dev/sdc
```

## Utilizzo di blktrace da Remoto

Poiché blktrace traccia le operazioni di I/O a blocchi e allo stesso tempo scrive normalmente i dati di tracciamento su un dispositivo a blocchi, e in generale poiché non è una buona idea utilizzare lo stesso dispositivo su cui il tracer scrive, blktrace offre un modo per tracciare senza alterare in alcun modo il dispositivo tracciato, fornendo supporto nativo per l'invio di tutti i dati di tracciamento tramite rete.

Per far funzionare blktrace in questa modalità, si avvia blktrace in modalità server sul sistema host, che memorizzerà i dati acquisiti:

```
$ blktrace -l
server: waiting for connections...
```

Sul sistema target che verrà tracciato, si avvia blktrace in modalità client con l'opzione -h per connettersi al sistema host, passando anche il dispositivo da tracciare:

```
root@crownbay:~# blktrace -d /dev/sdc -h 192.168.1.43
blktrace: connecting to 192.168.1.43
blktrace: connected!
```

Sul sistema host, si dovrebbe vedere quanto segue:

```
server: connection from 192.168.1.43
```

In un'altra shell, eseguire il carico di lavoro che si desidera tracciare:

```
root@crownbay:/media/sdc# rm linux-2.6.19.2.tar.bz2; wget https://downloads.
↳yoctoproject.org/mirror/sources/linux-2.6.19.2.tar.bz2; sync
Connecting to downloads.yoctoproject.org (140.211.169.59:80)
linux-2.6.19.2.tar.b 100% \|\|*****\| 41727k 0:00:00 ETA
```

Al termine, si preme Ctrl-C sul sistema target per interrompere la traccia:

```
^C=== sdc ===
CPU 0:          7691 events,      361 KiB data
CPU 1:          4109 events,      193 KiB data
Total:         11800 events (dropped 0), 554 KiB data
```

Sul sistema host, si dovrebbe anche vedere un riepilogo della traccia appena terminata:

```
server: end of run for 192.168.1.43:sdc
=== sdc ===
CPU 0:          7691 events,      361 KiB data
CPU 1:          4109 events,      193 KiB data
Total:         11800 events (dropped 0), 554 KiB data
```

L'istanza di blktrace sull'host salverà l'output del target in una directory <hostname>-<timestamp>:

```
$ ls -al
drwxr-xr-x 10 root root 1024 Oct 28 02:40 .
drwxr-sr-x  4 root root 1024 Oct 26 18:24 ..
drwxr-xr-x  2 root root 1024 Oct 28 02:40 192.168.1.43-2012-10-28-
↳02:40:56
```

Accedere a tale directory con cd per visualizzare i file di output:

```
$ ls -l
-rw-r--r--  1 root root 369193 Oct 28 02:44 sdc.blktrace.0
-rw-r--r--  1 root root 197278 Oct 28 02:44 sdc.blktrace.1
```

Eseguire blkparse sul sistema host utilizzando il nome del dispositivo:

```
$ blkparse sdc

8,32  1      1      0.000000000 1263 Q RM 6016 + 8 [ls]
8,32  1      0      0.000036038   0 m  N cfq1263 allocated
8,32  1      2      0.000039390 1263 G RM 6016 + 8 [ls]
8,32  1      3      0.000049168 1263 I RM 6016 + 8 [ls]
```

(continues on next page)

(continua dalla pagina precedente)

```

8,32  1      0      0.000056152      0 m  N cfq1263 insert_request
8,32  1      0      0.000061600      0 m  N cfq1263 add_to_rr
8,32  1      0      0.000075498      0 m  N cfq workload slice:300
.
.
.
8,32  0      0      177.266385696      0 m  N cfq1267 arm_idle: 8 group_idle: 0
8,32  0      0      177.266388140      0 m  N cfq schedule dispatch
8,32  1      0      177.266679239      0 m  N cfq1267 slice expired t=0
8,32  1      0      177.266689297      0 m  N cfq1267 sl_used=9 disp=6 charge=9
↪iops=0 sect=56
8,32  1      0      177.266692649      0 m  N cfq1267 del_from_rr
8,32  1      0      177.266696560      0 m  N cfq1267 put_queue

```

## CPU0 (sdc):

```

Reads Queued:      0,      0KiB      Writes Queued:      270,  21,
↪708KiB
Read Dispatches:   59,    2,628KiB      Write Dispatches:   495,  39,
↪964KiB
Reads Requeued:    0
Reads Completed:   90,    2,752KiB      Writes Completed:   543,  41,
↪596KiB
Read Merges:       0,      0KiB      Write Merges:       9,    ↪
↪344KiB
Read depth:        2
IO unplugs:        20
Timer unplugs:     1

```

## CPU1 (sdc):

```

Reads Queued:      688,    2,752KiB      Writes Queued:      381,  20,
↪652KiB
Read Dispatches:   31,    124KiB      Write Dispatches:   59,  2,
↪396KiB
Reads Requeued:    0
Reads Completed:   0,      0KiB      Writes Completed:   11,    ↪
↪764KiB
Read Merges:       598,    2,392KiB      Write Merges:       88,    ↪
↪448KiB
Read depth:        2
IO unplugs:        52
Timer unplugs:     0

```

## Total (sdc):

```

Reads Queued:      688,    2,752KiB      Writes Queued:      651,  42,
↪360KiB
Read Dispatches:   90,    2,752KiB      Write Dispatches:   554,  42,

```

(continues on next page)

(continua dalla pagina precedente)

```

↪360KiB
Reads Requeued:          0          Writes Requeued:          0
Reads Completed:        90,    2,752KiB    Writes Completed:    554,    42,
↪360KiB
Read Merges:            598,    2,392KiB    Write Merges:          97,    1
↪792KiB
IO unplugs:             72          Timer unplugs:          1

Throughput (R/W): 15KiB/s / 238KiB/s
Events (sdc): 9,301 entries
Skips: 0 forward (0 - 0.0%)

```

Si dovrebbero vedere gli eventi di traccia e il riepilogo esattamente come se fosse stato eseguito lo stesso comando sul target.

### Tracing dell'I/O a Blocchi tramite 'ftrace'

È anche possibile tracciare l'I/O a blocchi utilizzando solo *il sottosistema dei 'trace events'*, il che può essere utile per un tracing occasionale se non si desidera utilizzare gli strumenti nello spazio utente.

Per abilitare il tracing per un determinato dispositivo, utilizzare il comando `/sys/block/xxx/trace/enable`, dove `xxx` è il nome del dispositivo. Ad esempio, questo abilita il tracciamento per `/dev/sdc`:

```
root@crownbay:/sys/kernel/debug/tracing# echo 1 > /sys/block/sdc/trace/enable
```

Una volta selezionati i dispositivi che si desidera tracciare, selezionando il tracer `blk` si attiverà il tracer `blk`:

```

root@crownbay:/sys/kernel/debug/tracing# cat available_tracers
blk function_graph function nop

root@crownbay:/sys/kernel/debug/tracing# echo blk > current_tracer

```

Eseguire il carico di lavoro di interesse:

```
root@crownbay:/sys/kernel/debug/tracing# cat /media/sdc/testfile.txt
```

E osservare l'output (si noti che qui stiamo usando `trace_pipe` invece di `trace` per acquisire questa traccia: questo ci permette di attendere sulla pipe che i dati vengano visualizzati):

```

root@crownbay:/sys/kernel/debug/tracing# cat trace_pipe
cat-3587 [001] d..1 3023.276361: 8,32 Q R 1699848 + 8 [cat]
cat-3587 [001] d..1 3023.276410: 8,32 m N cfq3587 allocated
cat-3587 [001] d..1 3023.276415: 8,32 G R 1699848 + 8 [cat]
cat-3587 [001] d..1 3023.276424: 8,32 P N [cat]
cat-3587 [001] d..2 3023.276432: 8,32 I R 1699848 + 8 [cat]
cat-3587 [001] d..1 3023.276439: 8,32 m N cfq3587 insert_

```

(continues on next page)

(continua dalla pagina precedente)

```

↪request
    cat-3587  [001] d..1 3023.276445: 8,32 m N cfq3587 add_to_rr
    cat-3587  [001] d..2 3023.276454: 8,32 U N [cat] 1
    cat-3587  [001] d..1 3023.276464: 8,32 m N cfq workload_
↪slice:150
    cat-3587  [001] d..1 3023.276471: 8,32 m N cfq3587 set_active_
↪wl_prio:0 wl_type:2
    cat-3587  [001] d..1 3023.276478: 8,32 m N cfq3587 fifo= (null)
    cat-3587  [001] d..1 3023.276483: 8,32 m N cfq3587 dispatch_
↪insert
    cat-3587  [001] d..1 3023.276490: 8,32 m N cfq3587 dispatched a_
↪request
    cat-3587  [001] d..1 3023.276497: 8,32 m N cfq3587 activate rq,_
↪drv=1
    cat-3587  [001] d..2 3023.276500: 8,32 D R 1699848 + 8 [cat]

```

E questo disattiva il tracing per il dispositivo specificato:

```
root@crownbay:/sys/kernel/debug/tracing# echo 0 > /sys/block/sdc/trace/enable
```

## Documentazione di blktrace

Le versioni online delle pagine di manuale per i comandi discussi in questa sezione sono disponibili qui:

- [blktrace\(8\)](#)
- [blkparse\(1\)](#)
- [btrace\(8\)](#)

Le pagine di manuale sopra riportate, insieme ai manuali per le altre utilità di blktrace (btt, blkmon, ecc.) sono disponibili nella directory `/doc` del repository Git degli strumenti di blktrace:

```
$ git clone https://git.kernel.org/pub/scm/linux/kernel/git/axboe/blktrace.git
```

## 11.4 Esempi Pratici

Questo capitolo contiene esempi pratici.

### 11.4.1 Velocità di Scrittura Ridotta sulle Immagini Live

In una delle nostre precedenti versioni (denzil), gli utenti hanno notato che il boot da un'immagine live e la scrittura su disco erano notevolmente più lenti. Questo includeva il boot stesso, soprattutto il primo, poiché i primi boot tendono a eseguire una quantità significativa di operazioni di scrittura a causa di alcuni script post-installazione.

Il problema (e la soluzione) sono stati scoperti utilizzando i tool di tracing di Yocto, in questo caso 'perf stat', 'perf script', 'perf record' e 'perf report'.

Per tutti i dettagli su come questo bug è stato diagnosticato e risolto, consultare: Yocto Bug #3049

---

The Yocto Project ®

<docs@lists.yoctoproject.org>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.





---

## Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit (SDK/eSDK)

---

### 12.1 Introduzione

#### 12.1.1 SDK/eSDK Introduction

Welcome to the Yocto Project Application Development and Software Development Kits (SDK/eSDK) manual. This manual explains how to use both the Yocto Project extensible and standard SDKs to develop applications and images.

All SDKs consist of the following:

- *Cross-Development Toolchain*: This toolchain contains a compiler, debugger, and various associated tools.
- *Libraries, Headers, and Symbols*: The libraries, headers, and symbols are specific to the image (i.e. they match the image against which the SDK was built).
- *Environment Setup Script*: This `*.sh` file, once sourced, sets up the cross-development environment by defining variables and preparing for SDK use.

Additionally, an extensible SDK has tools that allow you to easily add new applications and libraries to an image, modify the source of an existing component, test changes on the target hardware, and easily integrate an application into the *OpenEmbedded Build System*.

You can use an SDK to independently develop and test code that is destined to run on some target machine. SDKs are completely self-contained. The binaries are linked against their own copy of `libc`, which results in no dependencies on the target system. To achieve this, the pointer to the dynamic loader is configured at install time since that path cannot be dynamically altered.

Another feature of the SDKs is that only one set of cross-compiler toolchain binaries are produced for any given architecture. This feature takes advantage of the fact that the target hardware can be passed to `gcc` as a set of compiler options. Those options are set up by the environment script and contained in variables such as `CC` and `LD`. This reduces the space needed for the tools. Understand, however, that every target still needs its own *sysroot* because those binaries are target-specific.

The SDK development environment consists of the following:

- The self-contained SDK, which is an architecture-specific cross-toolchain and matching sysroots (target and native) all built by the OpenEmbedded build system (e.g. the SDK). The toolchain and sysroots are based on a *Metadata* configuration and extensions, which allows you to cross-develop on the host machine for the target hardware. Additionally, the extensible SDK contains the `devtool` functionality.
- The Quick EMUlator (QEMU), which lets you simulate target hardware. QEMU is not literally part of the SDK. You must build and include this emulator separately. However, QEMU plays an important role in the development process that revolves around use of the SDK.

In summary, the extensible and standard SDK share many features. However, the extensible SDK has powerful development tools to help you more quickly develop applications. Here is a table that summarizes the primary differences between the standard and extensible SDK types when considering which to build:

| <i>Feature</i>               | <i>Standard SDK</i> | <i>Extensible SDK</i>                              |
|------------------------------|---------------------|----------------------------------------------------|
| Toolchain                    | Yes                 | Yes <sup>1</sup>                                   |
| Debugger                     | Yes                 | Yes <sup>1</sup>                                   |
| Size                         | 100+ MBytes         | 1+ GBytes (or 300+ MBytes for minimal w/toolchain) |
| <code>devtool</code>         | No                  | Yes                                                |
| Build Images                 | No                  | Yes                                                |
| Updateable                   | No                  | Yes                                                |
| Managed Sysroot <sup>2</sup> | No                  | Yes                                                |
| Installed Packages           | No <sup>3</sup>     | Yes <sup>4</sup>                                   |
| Construction                 | Packages            | Shared State                                       |

## The Cross-Development Toolchain

The *Cross-Development Toolchain* consists of a cross-compiler, cross-linker, and cross-debugger that are used to develop user-space applications for targeted hardware; in addition, the extensible SDK comes with built-in `devtool` functionality. This toolchain is created by running a SDK installer script or through a *Build Directory* that is based on your metadata configuration or extension for your targeted device. The cross-toolchain works with a matching target sysroot.

---

<sup>1</sup> Extensible SDK contains the toolchain and debugger if `SDK_EXT_TYPE` is "full" or `SDK_INCLUDE_TOOLCHAIN` is "1", which is the default.

<sup>2</sup> Sysroot is managed through the use of `devtool`. Thus, it is less likely that you will corrupt your SDK sysroot when you try to add additional libraries.

<sup>3</sup> You can add runtime package management to the standard SDK but it is not supported by default.

<sup>4</sup> You must build and make the shared state available to extensible SDK users for "packages" you want to enable users to install.

## Sysroots

The native and target *sysroots* contain needed headers and libraries for generating binaries that run on the target architecture. The target sysroot is based on the target root filesystem image that is built by the OpenEmbedded build system and uses the same metadata configuration used to build the cross-toolchain.

However, the extensible and standard SDKs *sysroots* differ in content:

- The standard SDK *sysroot* only contains libraries and headers for the packages --- and their dependencies --- found in the *TOOLCHAIN\_TARGET\_TASK* and *TOOLCHAIN\_HOST\_TASK* definitions, for the target and host *sysroots* respectively.

See *Obtaining the SDK* to learn how to build it and *Customizing the Standard SDK* to learn how to customize it.

- The extensible SDK *sysroot* is completely managed by the *devtool* command-line tool, and its content is the same as the *sysroot* of the image recipe for which the SDK was built.

See *Obtaining the SDK* to learn how to build it and *Customizing the Extensible SDK standalone installer* to learn how to customize it.


## The QEMU Emulator

The QEMU emulator allows you to simulate your hardware while running your application or image. QEMU is not part of the SDK but is automatically installed and available if you have done any one of the following:

- Setup your *Build Host* as described in the *Setting Up to Use the Yocto Project* section of the Yocto Project Development Tasks Manual.
- installed the cross-toolchain tarball and sourced the toolchain's setup environment script.

### 12.1.2 SDK Development Model

Fundamentally, the SDK fits into the development process as follows:



The SDK is installed on any machine and can be used to develop applications, images, and kernels. An SDK can even be used by a QA Engineer or Release Engineer. The fundamental concept is that the machine that has the SDK installed does not have to be associated with the machine that has the Yocto Project installed. A developer can independently compile and test an object on their machine and then, when the object is ready for integration into an image, they can simply make it available to the machine that has the Yocto Project. Once the object is available, the image can be rebuilt using the Yocto Project to produce the modified image.

You just need to follow these general steps:

1. *Install the SDK for your target hardware:* For information on how to install the SDK, see the "[Installing the SDK](#)" section.
2. *Download or Build the Target Image:* The Yocto Project supports several target architectures and has many pre-built kernel images and root filesystem images.

If you are going to develop your application on hardware, go to the [machines](#) download area and choose a target machine area from which to download the kernel image and root filesystem. This download area could have several files in it that support development using actual hardware. For example, the area might contain `.hddimg` files that combine the kernel image with the filesystem, boot loaders, and so forth. Be sure to get the files you need for your particular development process.

If you are going to develop your application and then run and test it using the QEMU emulator, go to the [machines/qemu](#) download area. From this area, go down into the directory for your target architecture (e.g. `qemux86_64` for an Intel-based 64-bit architecture). Download the kernel, root filesystem, and any other files you need for your process.

**i Nota**

To use the root filesystem in QEMU, you need to extract it. See the "*Extracting the Root Filesystem*" section for information on how to do this extraction.

3. *Develop and Test your Application*: At this point, you have the tools to develop your application. If you need to separately install and use the QEMU emulator, you can go to [QEMU Home Page](#) to download and learn about the emulator. See the "*Using the Quick EMUlator (QEMU)*" chapter in the Yocto Project Development Tasks Manual for information on using QEMU within the Yocto Project.

The remainder of this manual describes how to use the extensible and standard SDKs. There is also information in appendix form describing how you can build, install, and modify an SDK.

## 12.2 Using the Extensible SDK

This chapter describes the extensible SDK and how to install it. Information covers the pieces of the SDK, how to install it, and presents a look at using the `devtool` functionality. The extensible SDK makes it easy to add new applications and libraries to an image, modify the source for an existing component, test changes on the target hardware, and ease integration into the rest of the *OpenEmbedded Build System*.

**i Nota**

For a side-by-side comparison of main features supported for an extensible SDK as compared to a standard SDK, see the *Introduzione* section.

In addition to the functionality available through `devtool`, you can alternatively make use of the toolchain directly, for example from Makefile and Autotools. See the "*Using the SDK Toolchain Directly*" chapter for more information.

### 12.2.1 Why use the Extensible SDK and What is in It?

The extensible SDK provides a cross-development toolchain and libraries tailored to the contents of a specific image. You would use the Extensible SDK if you want a toolchain experience supplemented with the powerful set of `devtool` commands tailored for the Yocto Project environment.

The installed extensible SDK consists of several files and directories. Basically, it contains an SDK environment setup script, some configuration files, an internal build system, and the `devtool` functionality.

### 12.2.2 Installing the Extensible SDK

#### Two ways to install the Extensible SDK

Extensible SDK can be installed in two different ways, and both have their own pros and cons:

1. *Setting up the Extensible SDK environment directly in a Yocto build*. This avoids having to produce, test, distribute and maintain separate SDK installer archives, which can get very large. There is only one environment for the regular Yocto build and the SDK and less code paths where things can go not according to plan. It's easier to update the SDK: it simply means updating the Yocto layers with `git fetch` or layer management tooling. The

SDK extensibility is better than in the second option: just run `bitbake` again to add more things to the sysroot, or add layers if even more things are required.

2. *Setting up the Extensible SDK from a standalone installer.* This has the benefit of having a single, self-contained archive that includes all the needed binary artifacts. So nothing needs to be rebuilt, and there is no need to provide a well-functioning binary artefact cache over the network for developers with underpowered laptops.

### Setting up the Extensible SDK environment directly in a Yocto build

1. Set up all the needed layers and a Yocto *Build Directory*, e.g. a regular Yocto build where `bitbake` can be executed.
2. Run:

```
$ bitbake meta-ide-support
$ bitbake -c populate_sysroot gtk+3
# or any other target or native item that the application developer would need
$ bitbake build-sysroots -c build_native_sysroot && bitbake build-sysroots -c \
↳ build_target_sysroot
```

### Setting up the Extensible SDK from a standalone installer

The first thing you need to do is install the SDK on your *Build Host* by running the `*.sh` installation script.

You can download a tarball installer, which includes the pre-built toolchain, the `runqemu` script, the internal build system, `devtool`, and support files from the appropriate *toolchain* directory within the Index of Releases. Toolchains are available for several 32-bit and 64-bit architectures with the `x86_64` directories, respectively. The toolchains the Yocto Project provides are based off the `core-image-sato` and `core-image-minimal` images and contain libraries appropriate for developing against that image.

The names of the tarball installer scripts are such that a string representing the host system appears first in the filename and then is immediately followed by a string representing the target architecture. An extensible SDK has the string "-ext" as part of the name. Following is the general form:

```
poky-glibc-host_system-image_type-arch-toolchain-ext-release_version.sh
```

Dove:

- *host\_system* is a string representing your development system: `i686` or `x86_64`.
- *image\_type* is the image for which the SDK was built: `core-image-sato` or `core-image-minimal`.
- *arch* is a string representing the tuned target architecture: `aarch64`, `armv5e`, `core2-64`, `i586`, `mips32r2`, `mips64`, `ppc7400`, or `cortexa8hf-neon`.
- *release\_version* is a string representing the release number of the Yocto Project: `6.1`, `6.1+snapshot`.

For example, the following SDK installer is for a 64-bit development host system and a `i586`-tuned target architecture based off the SDK for `core-image-sato` and using the current 6.1 snapshot:

```
poky-glibc-x86_64-core-image-sato-i586-toolchain-ext-6.1.sh
```

**i Nota**

As an alternative to downloading an SDK, you can build the SDK installer. For information on building the installer, see the *Building an SDK Installer* section.

The SDK and toolchains are self-contained and by default are installed into the `poky_sdk` folder in your home directory. You can choose to install the extensible SDK in any location when you run the installer. However, because files need to be written under that directory during the normal course of operation, the location you choose for installation must be writable for whichever users need to use the SDK.

The following command shows how to run the installer given a toolchain tarball for a 64-bit x86 development host system and a 64-bit x86 target architecture. The example assumes the SDK installer is located in `~/Downloads/` and has execution rights:

```
$ ./Downloads/poky-glibc-x86_64-core-image-minimal-core2-64-toolchain-ext-2.5.sh
Poky (Yocto Project Reference Distro) Extensible SDK installer version 2.5
=====
Enter target directory for SDK (default: poky_sdk):
You are about to install the SDK to "/home/scottrif/poky_sdk". Proceed [Y/n]? Y
Extracting SDK.....done
Setting it up...
Extracting buildtools...
Preparing build system...
Parsing recipes: 100% |#####|
↪#####| Time: 0:00:52
Initialising tasks: 100% |#####|
↪#####| Time: 0:00:00
Checking sstate mirror object availability: 100% |#####|
↪#####| Time: 0:00:00
Loading cache: 100% |#####|
↪#####| Time: 0:00:00
Initialising tasks: 100% |#####|
↪#####| Time: 0:00:00
done
SDK has been successfully set up and is ready to be used.
Each time you wish to use the SDK in a new shell session, you need to source the
↪environment setup script e.g.
$ . /home/scottrif/poky_sdk/environment-setup-core2-64-poky-linux
```

**i Nota**

If you do not have write permissions for the directory into which you are installing the SDK, the installer notifies you and exits. For that case, set up the proper permissions in the directory and run the installer again.

### 12.2.3 Running the Extensible SDK Environment Setup Script

Once you have the SDK installed, you must run the SDK environment setup script before you can actually use the SDK.

When using an SDK directly in a Yocto build, you will find the script in `tmp/deploy/images/qemux86-64/` in your *Build Directory*.

When using a standalone SDK installer, this setup script resides in the directory you chose when you installed the SDK, which is either the default `poky_sdk` directory or the directory you chose during installation.

Before running the script, be sure it is the one that matches the architecture for which you are developing. Environment setup scripts begin with the string "environment-setup" and include as part of their name the tuned target architecture. As an example, the following commands set the working directory to where the SDK was installed and then source the environment setup script. In this example, the setup script is for an IA-based target machine using i586 tuning:

```
$ cd /home/scottrif/poky_sdk
$ source environment-setup-core2-64-poky-linux
SDK environment now set up; additionally you may now run devtool to perform
↳ development tasks.
Run devtool --help for further details.
```

When using the environment script directly in a Yocto build, it can be run similarly:

```
$ source tmp/deploy/images/qemux86-64/environment-setup-core2-64-poky-linux
```

Running the setup script defines many environment variables needed in order to use the SDK (e.g. `PATH`, `CC`, `LD`, and so forth). If you want to see all the environment variables the script exports, examine the installation file itself.

### 12.2.4 Using `devtool` in Your SDK Workflow

The cornerstone of the extensible SDK is a command-line tool called `devtool`. This tool provides a number of features that help you build, test and package software within the extensible SDK, and optionally integrate it into an image built by the OpenEmbedded build system.

**i Nota**

The use of `devtool` is not limited to the extensible SDK. You can use `devtool` to help you easily develop any project whose build output must be part of an image built using the build system.

The `devtool` command line is organized similarly to *Git* in that it has a number of sub-commands for each function. You can run `devtool --help` to see all the commands.



**i Nota**

See the "*devtool Quick Reference*" section in the Yocto Project Reference Manual.

`devtool` subcommands provide entry-points into development:

- *devtool add*: Assists in adding new software to be built.
- *devtool modify*: Sets up an environment to enable you to modify the source of an existing component.
- *devtool ide-sdk*: Generates a configuration for an IDE.
- *devtool upgrade*: Updates an existing recipe so that you can build it for an updated set of source files.

As with the build system, "recipes" represent software packages within `devtool`. When you use `devtool add`, a recipe is automatically created. When you use `devtool modify`, the specified existing recipe is used in order to determine where to get the source code and how to patch it. In both cases, an environment is set up so that when you build the recipe a source tree that is under your control is used in order to allow you to make changes to the source as desired. By default, new recipes and the source go into a "workspace" directory under the SDK.

To learn how to use `devtool` to add, modify, upgrade recipes and more, see the *Using the devtool command-line tool* section of the Yocto Project Development Tasks Manual.

## 12.2.5 Installing Additional Items Into the Extensible SDK

Out of the box the extensible SDK typically only comes with a small number of tools and libraries. A minimal SDK starts mostly empty and is populated on-demand. Sometimes you must explicitly install extra items into the SDK. If you need these extra items, you can first search for the items using the `devtool search` command. For example, suppose you need to link to `libGL` but you are not sure which recipe provides `libGL`. You can use the following command to find out:

```
$ devtool search libGL mesa
A free implementation of the OpenGL API
```

Once you know the recipe (i.e. `mesa` in this example), you can install it.

### When using the extensible SDK directly in a Yocto build

In this scenario, the Yocto build tooling, e.g. `bitbake` is directly accessible to build additional items, and it can simply be executed directly:

```
$ bitbake curl-native
# Add newly built native items to native sysroot
$ bitbake build-sysroots -c build_native_sysroot
$ bitbake mesa
# Add newly built target items to target sysroot
$ bitbake build-sysroots -c build_target_sysroot
```

## When using a standalone installer for the Extensible SDK

```
$ devtool sdk-install mesa
```

By default, the `devtool sdk-install` command assumes the item is available in pre-built form from your SDK provider. If the item is not available and it is acceptable to build the item from source, you can add the `-s` option as follows:

```
$ devtool sdk-install -s mesa
```

It is important to remember that building the item from source takes significantly longer than installing the pre-built artifact. Also, if there is no recipe for the item you want to add to the SDK, you must instead add the item using the `devtool add` command.

### 12.2.6 Applying Updates to an Installed Extensible SDK

If you are working with an installed extensible SDK that gets occasionally updated (e.g. a third-party SDK), then you will need to manually "pull down" the updates into the installed SDK.

To update your installed SDK, use `devtool` as follows:

```
$ devtool sdk-update
```

The previous command assumes your SDK provider has set the default update URL for you through the `SDK_UPDATE_URL` variable as described in the "[Providing Updates to the Extensible SDK After Installation](#)" section. If the SDK provider has not set that default URL, you need to specify it yourself in the command as follows:

```
$ devtool sdk-update path_to_update_directory
```

#### Nota

The URL needs to point specifically to a published SDK and not to an SDK installer that you would download and install.

### 12.2.7 Creating a Derivative SDK With Additional Components

You might need to produce an SDK that contains your own custom libraries. A good example would be if you were a vendor with customers that use your SDK to build their own platform-specific software and those customers need an SDK that has custom libraries. In such a case, you can produce a derivative SDK based on the currently installed SDK fairly easily by following these steps:

1. If necessary, install an extensible SDK that you want to use as a base for your derivative SDK.
2. Source the environment script for the SDK.
3. Add the extra libraries or other components you want by using the `devtool add` command.
4. Run the `devtool build-sdk` command.

The previous steps take the recipes added to the workspace and construct a new SDK installer that contains those recipes and the resulting binary artifacts. The recipes go into their own separate layer in the constructed derivative SDK, which leaves the workspace clean and ready for users to add their own recipes.

## 12.3 Using the Standard SDK

This chapter describes the standard SDK and how to install it. Information includes unique installation and setup aspects for the standard SDK.

### Nota

For a side-by-side comparison of main features supported for a standard SDK as compared to an extensible SDK, see the "*Introduzione*" section.

You can use a standard SDK to work on Makefile and Autotools-based projects. See the "*Using the SDK Toolchain Directly*" chapter for more information.

### 12.3.1 Why use the Standard SDK and What is in It?

The Standard SDK provides a cross-development toolchain and libraries tailored to the contents of a specific image. You would use the Standard SDK if you want a more traditional toolchain experience as compared to the extensible SDK, which provides an internal build system and the `devtool` functionality.

The installed Standard SDK consists of several files and directories. Basically, it contains an SDK environment setup script, some configuration files, and host and target root filesystems to support usage. You can see the directory structure in the "*Installed Standard SDK Directory Structure*" section.

### 12.3.2 Installing the SDK

The first thing you need to do is install the SDK on your *Build Host* by running the `*.sh` installation script.

You can download a tarball installer, which includes the pre-built toolchain, the `runqemu` script, and support files from the appropriate *toolchain* directory within the Index of Releases. Toolchains are available for several 32-bit and 64-bit architectures with the `x86_64` directories, respectively. The toolchains the Yocto Project provides are based off the `core-image-sato` and `core-image-minimal` images and contain libraries appropriate for developing against the corresponding image.

The names of the tarball installer scripts are such that a string representing the host system appears first in the filename and then is immediately followed by a string representing the target architecture:

```
poky-glibc-host_system-image_type-arch-toolchain-release_version.sh
```

Dove:

- *host\_system* is a string representing your development system: `i686` or `x86_64`.
- *image\_type* is the image for which the SDK was built: `core-image-minimal` or `core-image-sato`.
- *arch* is a string representing the tuned target architecture: `aarch64`, `armv5e`, `core2-64`, `i586`, `mips32r2`, `mips64`, `ppc7400`, or `cortexa8hf-neon`.

- *release\_version* is a string representing the release number of the Yocto Project: 6.1, 6.1+snapshot.

For example, the following SDK installer is for a 64-bit development host system and a i586-tuned target architecture based off the SDK for `core-image-sato` and the 6.1 release:

```
poky-glibc-x86_64-core-image-sato-i586-toolchain-6.1.sh
```

### Nota

As an alternative to downloading an SDK, you can build the SDK installer. For information on building the installer, see the "*Building an SDK Installer*" section.

The SDK and toolchains are self-contained and by default are installed into the `poky_sdk` folder in your home directory. You can choose to install the extensible SDK in any location when you run the installer. However, because files need to be written under that directory during the normal course of operation, the location you choose for installation must be writable for whichever users need to use the SDK.

The following command shows how to run the installer given a toolchain tarball for a 64-bit x86 development host system and a 64-bit x86 target architecture. The example assumes the SDK installer is located in `~/Downloads/` and has execution rights:

```
$ ./Downloads/poky-glibc-x86_64-core-image-sato-i586-toolchain-6.1.sh
Poky (Yocto Project Reference Distro) SDK installer version 6.1
=====
Enter target directory for SDK (default: /opt/poky/6.1):
You are about to install the SDK to "/opt/poky/6.1". Proceed [Y/n]? Y
Extracting SDK.....
↪..done
Setting it up...done
SDK has been successfully set up and is ready to be used.
Each time you wish to use the SDK in a new shell session, you need to source the
↪environment setup script e.g.
$ . /opt/poky/6.1/environment-setup-i586-poky-linux
```

**i Nota**

If you do not have write permissions for the directory into which you are installing the SDK, the installer notifies you and exits. For that case, set up the proper permissions in the directory and run the installer again.

Again, reference the "*Installed Standard SDK Directory Structure*" section for more details on the resulting directory structure of the installed SDK.

### 12.3.3 Running the SDK Environment Setup Script

Once you have the SDK installed, you must run the SDK environment setup script before you can actually use the SDK. This setup script resides in the directory you chose when you installed the SDK, which is either the default `/opt/poky/6.1` directory or the directory you chose during installation.

Before running the script, be sure it is the one that matches the architecture for which you are developing. Environment setup scripts begin with the string "environment-setup" and include as part of their name the tuned target architecture. As an example, the following commands set the working directory to where the SDK was installed and then source the environment setup script. In this example, the setup script is for an IA-based target machine using i586 tuning:

```
$ source /opt/poky/6.1/environment-setup-i586-poky-linux
```

When you run the setup script, the same environment variables are defined as are when you run the setup script for an extensible SDK. See the "*Installed Extensible SDK Directory Structure*" section for more information.


## 12.4 Using the SDK Toolchain Directly

You can use the SDK toolchain directly with Makefile and Autotools-based projects.

### 12.4.1 Autotools-Based Projects

Once you have a suitable *The Cross-Development Toolchain* installed, it is very easy to develop a project using the GNU Autotools-based workflow, which is outside of the *OpenEmbedded Build System*.

The following figure presents a simple Autotools workflow.



Follow these steps to create a simple Autotools-based "Hello World" project:

#### **Nota**

For more information on the GNU Autotools workflow, see the same example on the GNOME Developer site.

1. *Create a Working Directory and Populate It:* Create a clean directory for your project and then make that directory your working location:

```
$ mkdir $HOME/helloworld
$ cd $HOME/helloworld
```

After setting up the directory, populate it with files needed for the flow. You need a project source file, a file to help with configuration, and a file to help create the Makefile, and a README file: `hello.c`, `configure.ac`, `Makefile.am`, and `README`, respectively.

Use the following command to create an empty README file, which is required by GNU Coding Standards:

```
$ touch README
```

Create the remaining three files as follows:

- hello.c:

```
#include <stdio.h>

int main()
{
    printf("Hello World!\n");
    return 0;
}
```

- configure.ac:

```
AC_INIT(hello, 0.1)
AM_INIT_AUTOMAKE([foreign])
AC_PROG_CC
AC_CONFIG_FILES(Makefile)
AC_OUTPUT
```

- Makefile.am:

```
bin_PROGRAMS = hello
hello_SOURCES = hello.c
```

2. *Source the Cross-Toolchain Environment Setup File:* As described earlier in the manual, installing the cross-toolchain creates a cross-toolchain environment setup script in the directory that the SDK was installed. Before you can use the tools to develop your project, you must source this setup script. The script begins with the string "environment-setup" and contains the machine architecture, which is followed by the string "poky-linux". For this example, the command sources a script from the default SDK installation directory that uses the 32-bit Intel x86 Architecture and the 6.1 Yocto Project release:

```
$ source /opt/poky/6.1/environment-setup-i586-poky-linux
```

Another example is sourcing the environment setup directly in a Yocto build:

```
$ source tmp/deploy/images/qemux86-64/environment-setup-core2-64-poky-linux
```

3. *Create the configure Script:* Use the `autoreconf` command to generate the `configure` script:

```
$ autoreconf
```

The `autoreconf` tool takes care of running the other Autotools such as `aclocal`, `autoconf`, and `automake`.

**i Nota**

If you get errors from `configure.ac`, which `autoreconf` runs, that indicate missing files, you can use the `"-i"` option, which ensures missing auxiliary files are copied to the build host.

4. *Cross-Compile the Project:* This command compiles the project using the cross-compiler. The `CONFIGURE_FLAGS` environment variable provides the minimal arguments for GNU configure:

```
$ ./configure ${CONFIGURE_FLAGS}
```

For an Autotools-based project, you can use the cross-toolchain by just passing the appropriate host option to `configure.sh`. The host option you use is derived from the name of the environment setup script found in the directory in which you installed the cross-toolchain. For example, the host option for an ARM-based target that uses the GNU EABI is `armv5te-poky-linux-gnueabi`. You will notice that the name of the script is `environment-setup-armv5te-poky-linux-gnueabi`. Thus, the following command works to update your project and rebuild it using the appropriate cross-toolchain tools:

```
$ ./configure --host=armv5te-poky-linux-gnueabi --with-libtool-sysroot=sysroot_
↪dir
```

5. *Make and Install the Project:* These two commands generate and install the project into the destination directory:

```
$ make
$ make install DESTDIR=./tmp
```

**i Nota**

To learn about environment variables established when you run the cross-toolchain environment setup script and how they are used or overridden by the Makefile, see the *Makefile-Based Projects* section.

This next command is a simple way to verify the installation of your project. Running the command prints the architecture on which the binary file can run. This architecture should be the same architecture that the installed cross-toolchain supports:

```
$ file ./tmp/usr/local/bin/hello
```

6. *Execute Your Project:* To execute the project, you would need to run it on your target hardware. If your target hardware happens to be your build host, you could run the project as follows:

```
$ ./tmp/usr/local/bin/hello
```


As expected, the project displays the "Hello World!" message.



## 12.4.2 Makefile-Based Projects

Simple Makefile-based projects use and interact with the cross-toolchain environment variables established when you run the cross-toolchain environment setup script. The environment variables are subject to general `make` rules.

This section presents a simple Makefile development flow and provides an example that lets you see how you can use cross-toolchain environment variables and Makefile variables during development.



The main point of this section is to explain the following three cases regarding variable behavior:

- *Case 1 --- No Variables Set in the Makefile Map to Equivalent Environment Variables Set in the SDK Setup Script:* Because matching variables are not specifically set in the `Makefile`, the variables retain their values based on the environment setup script.
- *Case 2 --- Variables Are Set in the Makefile that Map to Equivalent Environment Variables from the SDK Setup Script:* Specifically setting matching variables in the `Makefile` during the build results in the environment settings of the variables being overwritten. In this case, the variables you set in the `Makefile` are used.
- *Case 3 --- Variables Are Set Using the Command Line that Map to Equivalent Environment Variables from the SDK Setup Script:* Executing the `Makefile` from the command line results in the environment variables being overwritten. In this case, the command-line content is used.

**i Nota**

Regardless of how you set your variables, if you use the "-e" option with `make`, the variables from the SDK setup script take precedence:

```
$ make -e target
```

The remainder of this section presents a simple Makefile example that demonstrates these variable behaviors.

In a new shell environment variables are not established for the SDK until you run the setup script. For example, the following commands show a null value for the compiler variable (i.e. `CC`):

```
$ echo ${CC}

$
```

Running the SDK setup script for a 64-bit build host and an i586-tuned target architecture for a `core-image-sato` image using the current 6.1 Yocto Project release and then echoing that variable shows the value established through the script:

```
$ source /opt/poky/6.1/environment-setup-i586-poky-linux
$ echo ${CC}
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/6.1/sysroots/i586-poky-
↳linux
```

To illustrate variable use, work through this simple "Hello World!" example:

1. *Create a Working Directory and Populate It:* Create a clean directory for your project and then make that directory your working location:

```
$ mkdir $HOME/helloworld
$ cd $HOME/helloworld
```

After setting up the directory, populate it with files needed for the flow. You need a `main.c` file from which you call your function, a `module.h` file to contain headers, and a `module.c` that defines your function.

Create the three files as follows:

- `main.c`:

```
#include "module.h"
void sample_func();
int main()
{
    sample_func();
    return 0;
}
```

- `module.h`:

```
#include <stdio.h>

void sample_func();
```

- module.c:

```
#include "module.h"

void sample_func()
{
    printf("Hello World!");
    printf("\n");
}
```

2. *Source the Cross-Toolchain Environment Setup File:* As described earlier in the manual, installing the cross-toolchain creates a cross-toolchain environment setup script in the directory that the SDK was installed. Before you can use the tools to develop your project, you must source this setup script. The script begins with the string "environment-setup" and contains the machine architecture, which is followed by the string "poky-linux". For this example, the command sources a script from the default SDK installation directory that uses the 32-bit Intel x86 Architecture and the Blacksail Yocto Project release:

```
$ source /opt/poky/6.1/environment-setup-i586-poky-linux
```

Another example is sourcing the environment setup directly in a Yocto build:

```
$ source tmp/deploy/images/qemux86-64/environment-setup-core2-64-poky-linux
```

3. *Create the Makefile:* For this example, the Makefile contains two lines that can be used to set the `CC` variable. One line is identical to the value that is set when you run the SDK environment setup script, and the other line sets `CC` to "gcc", the default GNU compiler on the build host:

```
# CC=i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/
↪ i586-poky-linux
# CC="gcc"
all: main.o module.o
    ${CC} main.o module.o -o target_bin
main.o: main.c module.h
    ${CC} -I . -c main.c
module.o: module.c module.h
    ${CC} -I . -c module.c
clean:
    rm -rf *.o
    rm target_bin
```

4. *Make the Project:* Use the `make` command to create the binary output file. Because variables are commented out in the Makefile, the value used for `CC` is the value set when the SDK environment setup file was run:

```
$ make
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux -I . -c main.c
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux -I . -c module.c
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux main.o module.o -o target_bin
```

From the results of the previous command, you can see that the compiler used was the compiler established through the `CC` variable defined in the setup script.

You can override the `CC` environment variable with the same variable as set from the Makefile by uncommenting the line in the Makefile and running `make` again:

```
$ make clean
rm -rf *.o
rm target_bin
#
# Edit the Makefile by uncommenting the line that sets CC to "gcc"
#
$ make
gcc -I . -c main.c
gcc -I . -c module.c
gcc main.o module.o -o target_bin
```

As shown in the previous example, the cross-toolchain compiler is not used. Rather, the default compiler is used.

This next case shows how to override a variable by providing the variable as part of the command line. Go into the Makefile and re-insert the comment character so that running `make` uses the established SDK compiler. However, when you run `make`, use a command-line argument to set `CC` to "gcc":

```
$ make clean
rm -rf *.o
rm target_bin
#
# Edit the Makefile to comment out the line setting CC to "gcc"
#
$ make
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux -I . -c main.c
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux -I . -c module.c
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux main.o module.o -o target_bin
$ make clean
```

(continues on next page)

(continua dalla pagina precedente)

```
rm -rf *.o
rm target_bin
$ make CC="gcc"
gcc -I . -c main.c
gcc -I . -c module.c
gcc main.o module.o -o target_bin
```

In the previous case, the command-line argument overrides the SDK environment variable.

In this last case, edit Makefile again to use the "gcc" compiler but then use the "-e" option on the `make` command line:

```
$ make clean
rm -rf *.o
rm target_bin
#
# Edit the Makefile to use "gcc"
#
$ make
gcc -I . -c main.c
gcc -I . -c module.c
gcc main.o module.o -o target_bin
$ make clean
rm -rf *.o
rm target_bin
$ make -e
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux -I . -c main.c
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux -I . -c module.c
i586-poky-linux-gcc -m32 -march=i586 --sysroot=/opt/poky/2.5/sysroots/i586-
↳poky-linux main.o module.o -o target_bin
```

In the previous case, the "-e" option forces `make` to use the SDK environment variables regardless of the values in the Makefile.

5. *Execute Your Project:* To execute the project (i.e. `target_bin`), use the following command:

```
$ ./target_bin
Hello World!
```

#### Nota

If you used the cross-toolchain compiler to build `target_bin` and your build host differs in architecture from that of the target machine, you need to run your project on the target device.

As expected, the project displays the "Hello World!" message.

## 12.5 Obtaining the SDK

### 12.5.1 Working with the SDK components directly in a Yocto build

Please refer to section "*Setting up the Extensible SDK environment directly in a Yocto build*"

Note that to use this feature effectively either a powerful build machine, or a well-functioning sstate cache infrastructure is required: otherwise significant time could be spent waiting for components to be built by BitBake from source code.

### 12.5.2 Working with standalone SDK Installers

#### Locating Pre-Built SDK Installers

You can use existing, pre-built toolchains by locating and running an SDK installer script that ships with the Yocto Project. Using this method, you select and download an architecture-specific SDK installer and then run the script to hand-install the toolchain.

Follow these steps to locate and hand-install the toolchain:

1. *Go to the Installers Directory:* Go to [https://downloads.yoctoproject.org/releases/yocto/yocto-6.1\\_M3/toolchain/](https://downloads.yoctoproject.org/releases/yocto/yocto-6.1_M3/toolchain/)
2. *Open the Folder for Your Build Host:* Open the folder that matches your *Build Host* (i.e. `i686` for 32-bit machines or `x86_64` for 64-bit machines).
3. *Locate and Download the SDK Installer:* You need to find and download the installer appropriate for your build host, target hardware, and image type.

The installer files (`*.sh`) follow this naming convention:

```
poky-glibc-host_system-core-image-type-arch-toolchain[-ext]-release.sh
```

With:

- *host\_system*: string representing your development system: `i686` or `x86_64`
- *type*: string representing the image: `sato` or `minimal`
- *arch*: string representing the target architecture such as `cortexa57-qemuarm64`
- *release*: version of the Yocto Project.

#### Nota

The standard SDK installer does not have the `-ext` string as part of the filename.

The toolchains provided by the Yocto Project are based off of the `core-image-sato` and `core-image-minimal` images and contain libraries appropriate for developing against those images.

For example, if your build host is a 64-bit x86 system and you need an extended SDK for a 64-bit core2 QEMU target, go into the `x86_64` folder and download the following installer:

```
poky-glibc-x86_64-core-image-sato-core2-64-qemux86-64-toolchain-6.1.sh
```

4. *Run the Installer:* Be sure you have execution privileges and run the installer. Here is an example from the Downloads directory:

```
$ ~/Downloads/poky-glibc-x86_64-core-image-sato-core2-64-qemux86-64-toolchain-
↳ 6.1.sh
```

During execution of the script, you choose the root location for the toolchain. See the "[Installed Standard SDK Directory Structure](#)" section and the "[Installed Extensible SDK Directory Structure](#)" section for more information.

## Building an SDK Installer

As an alternative to locating and downloading an SDK installer, you can build the SDK installer. Follow these steps:

1. *Set Up the Build Environment:* Be sure you are set up to use BitBake in a shell. See the "[Setting Up to Use the Yocto Project](#)" section in the Yocto Project Development Tasks Manual for information on how to get a *build host* ready.
2. *Make Sure You Are Building an Installer for the Correct Machine:* Check to be sure that your *MACHINE* matches the architecture for which you are building.
3. *Make Sure Your SDK Machine is Correctly Set:* If you are building a toolchain designed to run on an architecture that differs from your current development host machine (i.e. the build host), be sure that the *SDKMACHINE* variable is correctly set.

### Nota

If you are building an SDK installer for the Extensible SDK, the *SDKMACHINE* value must be set for the architecture of the machine you are using to build the installer. If *SDKMACHINE* is not set appropriately, the build fails and provides an error message similar to the following:

```
The extensible SDK can currently only be built for the same
architecture as the machine being built on - SDK_ARCH
is set to i686 (likely via setting SDKMACHINE) which is
different from the architecture of the build machine (x86_64).
Unable to continue.
```

4. *Build the SDK Installer:* To build the SDK installer for a standard SDK and populate the SDK image, use the following command form. Be sure to replace *image* with an image (e.g. "core-image-sato"):

```
$ bitbake image -c populate_sdk
```

You can do the same for the extensible SDK using this command form:

```
$ bitbake image -c populate_sdk_ext
```

These commands produce an SDK installer that contains the sysroot that matches your target root filesystem.

When the `bitbake` command completes, the SDK installer will be in `tmp/deploy/sdk` in the *Build Directory*.

**Nota**

- By default, the previous BitBake command does not build static binaries. If you want to use the toolchain to build these types of libraries, you need to be sure your SDK has the appropriate static development libraries. Use the `TOOLCHAIN_TARGET_TASK` variable to install the appropriate library packages as part of the SDK. Here is an example using `libc` static development libraries:

```
TOOLCHAIN_TARGET_TASK:append = " libc-staticdev"
```

5. *Run the Installer:* You can now run the SDK installer from `tmp/deploy/sdk` in the *Build Directory*. Here is an example:

```
$ cd bitbake-builds/build/tmp/deploy/sdk
$ ./poky-glibc-x86_64-core-image-sato-core2-64-toolchain-ext-6.1.sh
```

During execution of the script, you choose the root location for the toolchain. See the "*Installed Standard SDK Directory Structure*" section and the "*Installed Extensible SDK Directory Structure*" section for more information.

### 12.5.3 Extracting the Root Filesystem

After installing the toolchain, for some use cases you might need to separately extract a root filesystem:

- You want to boot the image using NFS.
- You want to use the root filesystem as the target sysroot.
- You want to develop your target application using the root filesystem as the target sysroot.

Follow these steps to extract the root filesystem:

1. *Locate and Download the Tarball for the Pre-Built Root Filesystem Image File:* You need to find and download the root filesystem image file that is appropriate for your target system. These files are kept in machine-specific folders in the *Index of Releases* in the "machines" directory.

The machine-specific folders of the "machines" directory contain tarballs (`*.tar.bz2`) for supported machines. These directories also contain flattened root filesystem image files (`*.ext4`), which you can use with QEMU directly.

The pre-built root filesystem image files follow this naming convention:

```
core-image-profile-machine.tar.bz2
```

With:

- *profile*: filesystem image's profile, such as `minimal`, `minimal-dev` or `sato`. For information on these types of image profiles, see the "Images" chapter in the Yocto Project Reference Manual.
- *machine*: same string as the name of the parent download directory.



The root filesystems provided by the Yocto Project are based off of the `core-image-sato` and `core-image-minimal` images.

For example, if you plan on using a BeagleBone device as your target hardware and your image is a `core-image-sato-sdk` image, you can download the following file:

```
core-image-sato-sdk-beaglebone-yocto.tar.bz2
```

2. *Initialize the Cross-Development Environment:* You must `source` the cross-development environment setup script to establish necessary environment variables.

This script is located in the top-level directory in which you installed the toolchain (e.g. `poky_sdk`).

Here is an example based on the toolchain installed in the "*Locating Pre-Built SDK Installers*" section:

```
$ source poky_sdk/environment-setup-core2-64-poky-linux
```

3. *Extract the Root Filesystem:* Use the `runqemu-extract-sdk` command and provide the root filesystem image.

Here is an example command that extracts the root filesystem from a previously built root filesystem image that was downloaded from the [Index of Releases](#). This command extracts the root filesystem into the `core2-64-sato` directory:

```
$ runqemu-extract-sdk ~/Downloads/core-image-sato-sdk-beaglebone-yocto.tar.bz2
↳ ~/beaglebone-sato
```

You could now point to the target sysroot at `beaglebone-sato`.

## 12.5.4 Installed Standard SDK Directory Structure

After you install the Standard SDK by running the `*.sh` SDK installation script, the following directory structure should be observed:

```
install_dir/version/
├─ buildinfo
├─ environment-setup-target-poky-linux
├─ site-config-target-poky-linux
├─ sysroots/
│   └─ target-poky-linux/
│       ├── bin/
│       ├── boot/
│       ├── etc/
│       ├── home/
│       ├── lib/
│       ├── media/
│       ├── mnt/
│       ├── proc/
│       ├── run/
│       ├── sbin/
│       └── sys/
```

```
| | └─ tmp/
| | └─ usr/
| | └─ var/
| └─ host-pokysdk-linux/
|   └─ bin/
|   └─ environment-setup.d/
|   └─ etc/
|   └─ lib/
|   └─ sbin/
|   └─ usr/
|   └─ var/
└─ version-target-poky-linux
```

The installed SDK consists of an environment setup script for the SDK, a configuration file for the target, a version file for the target, and the root filesystem (`sysroots`) needed to develop objects for the target system.

In the layout above, italicized text is used to indicate replaceable portions of the file or directory name. For example, *install\_dir/version* is the directory where the SDK is installed. By default, *install\_dir* is `/opt/poky/`. And, *version* represents the specific snapshot of the SDK (e.g. 6.1). Furthermore, *target* represents the target architecture (e.g. i586) and *host* represents the development system's architecture (e.g. x86\_64). Thus, the complete names of the two directories within the `sysroots` could be `i586-poky-linux` and `x86_64-pokysdk-linux` for the target and host, respectively.

## 12.5.5 Installed Extensible SDK Directory Structure

After you install the Extensible SDK by running the `*.sh` SDK installation script, the following directory structure should be observed:

```
install_dir/
├─ bitbake-cookerdaemon.log
├─ buildinfo
├─ buildtools/
├─ cache/
├─ conf/
├─ .devtoolbase
├─ downloads/
├─ environment-setup-target-poky-linux
├─ layers/
├─ oe-time-dd-test.dat
├─ preparing_system_build.log
├─ site-config-target-poky-linux
├─ sstate-cache/
├─ sysroots/
├─ tmp/
├─ version-target-poky-linux
└─ workspace/
```

The installed directory structure for the extensible SDK is quite different than the installed structure for the standard SDK. The extensible SDK does not separate host and target parts in the same manner as does the standard SDK. The extensible SDK uses an embedded copy of the OpenEmbedded build system, which has its own sysroots.

Of note in the directory structure are an environment setup script for the SDK, a configuration file for the target, a version file for the target, and log files for the OpenEmbedded build system preparation script run by the installer and BitBake.

In the layout above, italicized text is used to indicate replaceable portions of the file or directory name. For example, *install\_dir* is the directory where the SDK is installed, which is by default `poky_sdk` in your home directory and *target* represents the target architecture (e.g. `i586`).

## 12.6 Customizing the Extensible SDK standalone installer

This appendix describes customizations you can apply to the extensible SDK when using in the standalone installer version.

### Nota

It is also possible to use the Extensible SDK functionality directly in a Yocto build, avoiding separate installer artefacts. Please refer to "*Installing the Extensible SDK*"

### 12.6.1 Configuring the Extensible SDK

The extensible SDK primarily consists of a pre-configured copy of the OpenEmbedded build system from which it was produced. Thus, the SDK's configuration is derived using that build system and the filters shown in the following list. When these filters are present, the OpenEmbedded build system applies them against *build/conf/local.conf* and *build/conf/auto.conf*:

- Variables whose values start with "/" are excluded since the assumption is that those values are paths that are likely to be specific to the *Build Host*.
- Variables listed in *ESDK\_LOCALCONF\_REMOVE* are excluded. These variables are not allowed through from the OpenEmbedded build system configuration into the extensible SDK configuration. Typically, these variables are specific to the machine on which the build system is running and could be problematic as part of the extensible SDK configuration.

For a list of the variables excluded by default, see the *ESDK\_LOCALCONF\_REMOVE* in the glossary of the Yocto Project Reference Manual.

- Variables listed in *ESDK\_LOCALCONF\_ALLOW* are included. Including a variable in the value of *ESDK\_LOCALCONF\_ALLOW* overrides either of the previous two filters. The default value is blank.
- Classes inherited globally with *INHERIT* that are listed in *ESDK\_CLASS\_INHERIT\_DISABLE* are disabled. Using *ESDK\_CLASS\_INHERIT\_DISABLE* to disable these classes is the typical method to disable classes that are problematic or unnecessary in the SDK context. The default value disables the *buildhistory* class.

Additionally, the contents of `conf/sdk-extra.conf`, when present, are appended to the end of *build/conf/local.conf* within the produced SDK, without any filtering. The `sdk-extra.conf` file is particu-

larly useful if you want to set a variable value just for the SDK and not the OpenEmbedded build system used to create the SDK.

## 12.6.2 Adjusting the Extensible SDK to Suit Your Build Host's Setup

In most cases, the extensible SDK defaults should work with your *Build Host*'s setup. However, there are cases when you might consider making adjustments:

- If your SDK configuration inherits additional classes using the *INHERIT* variable and you do not need or want those classes enabled in the SDK, you can disable them by adding them to the *ESDK\_CLASS\_INHERIT\_DISABLE* variable as described in the previous section.

### Nota

The default value of *ESDK\_CLASS\_INHERIT\_DISABLE* is set using the "!=" operator. Consequently, you will need to either define the entire list by using the "=" operator, or you will need to append a value using either ":append" or the "+=" operator. You can learn more about these operators in the "Basic Syntax" section of the BitBake User Manual.

- If you have classes or recipes that add additional tasks to the standard build flow (i.e. the tasks execute as the recipe builds as opposed to being called explicitly), then you need to do one of the following:
  - After ensuring the tasks are *shared state* tasks (i.e. the output of the task is saved to and can be restored from the shared state cache) or ensuring the tasks are able to be produced quickly from a task that is a shared state task, add the task name to the value of *SDK\_RECRDEP\_TASKS*.
  - Disable the tasks if they are added by a class and you do not need the functionality the class provides in the extensible SDK. To disable the tasks, add the class to the *ESDK\_CLASS\_INHERIT\_DISABLE* variable as described in the previous section.
- Generally, you want to have a shared state mirror set up so users of the SDK can add additional items to the SDK after installation without needing to build the items from source. See the "*Providing Additional Installable Extensible SDK Content*" section for information.
- If you want users of the SDK to be able to easily update the SDK, you need to set the *SDK\_UPDATE\_URL* variable. For more information, see the "*Providing Updates to the Extensible SDK After Installation*" section.
- If you have adjusted the list of files and directories that appear in *COREBASE* (other than layers that are enabled through *build/conf/bblayers.conf*), then you must list these files in *COREBASE\_FILES* so that the files are copied into the SDK.
- If your OpenEmbedded build system setup uses a different environment setup script other than *oe-init-build-env*, then you must set *OE\_INIT\_ENV\_SCRIPT* to point to the environment setup script you use.

### Nota

You must also reflect this change in the value used for the *COREBASE\_FILES* variable as previously described.

### 12.6.3 Changing the Extensible SDK Installer Title

You can change the displayed title for the SDK installer by setting the `SDK_TITLE` variable and then rebuilding the SDK installer. For information on how to build an SDK installer, see the "[Building an SDK Installer](#)" section.

By default, this title is derived from `DISTRO_NAME` when it is set. If the `DISTRO_NAME` variable is not set, the title is derived from the `DISTRO` variable.

The `populate_sdk_base` class defines the default value of the `SDK_TITLE` variable as follows:

```
SDK_TITLE ??= "${@d.getVar('DISTRO_NAME') or d.getVar('DISTRO')} SDK"
```

While there are several ways of changing this variable, an efficient method is to set the variable in your distribution's configuration file. Doing so creates an SDK installer title that applies across your distribution. As an example, assume you have your own layer for your distribution named "meta-mydistro" and you are using the same type of file hierarchy as does the default "poky" distribution. If so, you could update the `SDK_TITLE` variable in the `~/meta-mydistro/conf/distro/mydistro.conf` file using the following form:

```
SDK_TITLE = "your_title"
```

### 12.6.4 Providing Updates to the Extensible SDK After Installation

When you make changes to your configuration or to the metadata and if you want those changes to be reflected in installed SDKs, you need to perform additional steps. These steps make it possible for anyone using the installed SDKs to update the installed SDKs by using the `devtool sdk-update` command:

1. Create a directory that can be shared over HTTP or HTTPS. You can do this by setting up a web server such as an [Apache HTTP Server](#) or [Nginx](#) server in the cloud to host the directory. This directory must contain the published SDK.
2. Set the `SDK_UPDATE_URL` variable to point to the corresponding HTTP or HTTPS URL. Setting this variable causes any SDK built to default to that URL and thus, the user does not have to pass the URL to the `devtool sdk-update` command as described in the "[Applying Updates to an Installed Extensible SDK](#)" section.
3. Build the extensible SDK normally (i.e., use the `bitbake -c populate_sdk_ext imagename` command).
4. Publish the SDK using the following command:

```
$ oe-publish-sdk some_path/sdk-installer.sh path_to_shared_http_directory
```

You must repeat this step each time you rebuild the SDK with changes that you want to make available through the update mechanism.

Completing the above steps allows users of the existing installed SDKs to simply run `devtool sdk-update` to retrieve and apply the latest updates. See the "[Applying Updates to an Installed Extensible SDK](#)" section for further information.

## 12.6.5 Changing the Default SDK Installation Directory

When you build the installer for the Extensible SDK, the default installation directory for the SDK is based on the *DISTRO* and *SDKEXTPATH* variables from within the *populate\_sdk\_base* class as follows:

```
SDKEXTPATH ??= "~/${@d.getVar('DISTRO')}_sdk"
```

You can change this default installation directory by specifically setting the *SDKEXTPATH* variable.

While there are several ways of setting this variable, the method that makes the most sense is to set the variable in your distribution's configuration file. Doing so creates an SDK installer default directory that applies across your distribution. As an example, assume you have your own layer for your distribution named "meta-mydistro" and you are using the same type of file hierarchy as does the default "poky" distribution. If so, you could update the *SDKEXTPATH* variable in the `~/meta-mydistro/conf/distro/mydistro.conf` file using the following form:

```
SDKEXTPATH = "some_path_for_your_installed_sdk"
```

After building your installer, running it prompts the user for acceptance of the `some_path_for_your_installed_sdk` directory as the default location to install the Extensible SDK.

## 12.6.6 Providing Additional Installable Extensible SDK Content

If you want the users of an extensible SDK you build to be able to add items to the SDK without requiring the users to build the items from source, you need to do a number of things:

1. Ensure the additional items you want the user to be able to install are already built:
  - Build the items explicitly. You could use one or more "meta" recipes that depend on lists of other recipes.
  - Build the "world" target and set `EXCLUDE_FROM_WORLD:pn-recipeName` for the recipes you do not want built. See the *EXCLUDE\_FROM\_WORLD* variable for additional information.
2. Expose the `sstate-cache` directory produced by the build. Typically, you expose this directory by making it available through an [Apache HTTP Server](#) or [Nginx](#) server.
3. Set the appropriate configuration so that the produced SDK knows how to find the configuration. The variable you need to set is *SSTATE\_MIRRORS*:

```
SSTATE_MIRRORS = "file://.* https://example.com/some_path/sstate-cache/PATH"
```

You can set the *SSTATE\_MIRRORS* variable in two different places:

- If the mirror value you are setting is appropriate to be set for both the OpenEmbedded build system that is actually building the SDK and the SDK itself (i.e. the mirror is accessible in both places or it will fail quickly on the OpenEmbedded build system side, and its contents will not interfere with the build), then you can set the variable in your *build/conf/local.conf* or custom distro configuration file. You can then pass the variable to the SDK by adding the following:

```
ESDK_LOCALCONF_ALLOW = "SSTATE_MIRRORS"
```

- Alternatively, if you just want to set the `SSTATE_MIRRORS` variable's value for the SDK alone, create a `conf/sdk-extra.conf` file either in your *Build Directory* or within any layer and put your `SSTATE_MIRRORS` setting within that file.

**Nota**

This second option is the safest option should you have any doubts as to which method to use when setting `SSTATE_MIRRORS`

## 12.6.7 Minimizing the Size of the Extensible SDK Installer Download

By default, the extensible SDK bundles the shared state artifacts for everything needed to reconstruct the image for which the SDK was built. This bundling can lead to an SDK installer file that is a Gigabyte or more in size. If the size of this file causes a problem, you can build an SDK that has just enough in it to install and provide access to the `devtool` command by setting the following in your configuration:

```
SDK_EXT_TYPE = "minimal"
```

Setting `SDK_EXT_TYPE` to "minimal" produces an SDK installer that is around 35 Mbytes in size, which downloads and installs quickly. You need to realize, though, that the minimal installer does not install any libraries or tools out of the box. These libraries and tools must be installed either "on the fly" or through actions you perform using `devtool` or explicitly with the `devtool sdk-install` command.

In most cases, when building a minimal SDK you need to also enable bringing in the information on a wider range of packages produced by the system. Requiring this wider range of information is particularly true so that `devtool add` is able to effectively map dependencies it discovers in a source tree to the appropriate recipes. Additionally, the information enables the `devtool search` command to return useful results.

To facilitate this wider range of information, you would need to set the following:

```
SDK_INCLUDE_PKGDATA = "1"
```

See the `SDK_INCLUDE_PKGDATA` variable for additional information.

Setting the `SDK_INCLUDE_PKGDATA` variable as shown causes the "world" target to be built so that information for all of the recipes included within it are available. Having these recipes available increases build time significantly and increases the size of the SDK installer by 30-80 Mbytes depending on how many recipes are included in your configuration.

You can use `EXCLUDE_FROM_WORLD:pn-recipeName` for recipes you want to exclude. However, it is assumed that you would need to be building the "world" target if you want to provide additional items to the SDK. Consequently, building for "world" should not represent undue overhead in most cases.

**i Nota**

If you set `SDK_EXT_TYPE` to "minimal", then providing a shared state mirror is mandatory so that items can be installed as needed. See the *Providing Additional Installable Extensible SDK Content* section for more information.

You can explicitly control whether or not to include the toolchain when you build an SDK by setting the `SDK_INCLUDE_TOOLCHAIN` variable to "1". In particular, it is useful to include the toolchain when you have set `SDK_EXT_TYPE` to "minimal", which by default, excludes the toolchain. Also, it is helpful if you are building a small SDK for use with an IDE or some other tool where you do not want to take extra steps to install a toolchain.

## 12.7 Customizing the Standard SDK

This appendix presents customizations you can apply to the standard SDK.

### 12.7.1 Adding Individual Packages to the Standard SDK

When you build a standard SDK using the `bitbake -c populate_sdk`, a default set of packages is included in the resulting SDK. The `TOOLCHAIN_HOST_TASK` and `TOOLCHAIN_TARGET_TASK` variables control the set of packages adding to the SDK.

If you want to add individual packages to the toolchain that runs on the host, simply add those packages to the `TOOLCHAIN_HOST_TASK` variable. Similarly, if you want to add packages to the default set that is part of the toolchain that runs on the target, add the packages to the `TOOLCHAIN_TARGET_TASK` variable.

### 12.7.2 Adding API Documentation to the Standard SDK

You can include API documentation as well as any other documentation provided by recipes with the standard SDK by adding "api-documentation" to the `DISTRO_FEATURES` variable:

```
DISTRO_FEATURES:append = " api-documentation"
```

Setting this variable as shown here causes the OpenEmbedded build system to build the documentation and then include it in the standard SDK.

---

The Yocto Project ®

<docs@lists.yoctoproject.org>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.



### 13.1 Introduzione

Toaster è un'interfaccia web per il *OpenEmbedded Build System* di Yocto Project. L'interfaccia consente di configurare ed eseguire le build. Le informazioni relative alle build vengono raccolte e memorizzate in un database. È possibile utilizzare Toaster per configurare e avviare build su più server di build remoti.

#### 13.1.1 Funzionalità di Toaster

Toaster consente di configurare ed eseguire build e fornisce informazioni dettagliate sul processo di build.

- *Configurazione ed Esecuzione delle Build:* È possibile utilizzare l'interfaccia web di Toaster per configurare e avviare le build. Le build avviate tramite l'interfaccia web di Toaster sono organizzate in progetti. Quando si crea un progetto, viene richiesto di selezionare una release, ovvero una versione del sistema di build, da utilizzare per le build del progetto. Toaster supporta le release di Yocto Project dalla 1.8 in poi. Tramite l'interfaccia web di Toaster, è possibile:
  - Esplorare i layer elencati nelle varie *sorgenti di layer* disponibili nel progetto (ad esempio, l'indice dei layer OpenEmbedded all'indirizzo <https://layers.openembedded.org/>).
  - Esplorare immagini, ricette e macchine fornite da tali layer.
  - Importare i propri layer per la compilazione.
  - Aggiungere e rimuovere layer dalla configurazione.
  - Impostare le variabili di configurazione.
  - Selezionare uno o più target da compilare.

- Avviare le build.

Toaster consente inoltre di configurare ed eseguire le build [compilazioni] dalla riga di comando e di passare dalla riga di comando all'interfaccia web in qualsiasi momento. Le compilazioni avviate dalla riga di comando vengono visualizzate in un progetto Toaster speciale denominato "Command line builds" [Compilazioni da riga di comando].

- *Informazioni sul Processo di Build:* Toaster registra anche informazioni dettagliate sulle build. Toaster raccoglie dati per le build avviate dall'interfaccia web e dalla riga di comando, a condizione che Toaster sia in esecuzione.

#### **Nota**

È necessario avviare Toaster prima della build, altrimenti non raccoglierà i dati.

Con Toaster è possibile:


- Visualizzare cosa è stato compilato (ricette e pacchetti) e quali pacchetti sono stati installati nell'immagine finale.
- Esplorare la struttura delle directory dell'immagine.
- Visualizzare il valore di tutte le variabili nella configurazione di build e quali file impostano ciascun valore.
- Esaminare i messaggi di errore, warning e trace [traccia] per facilitare il debug.
- Visualizzare informazioni sui task di BitBake eseguiti e riutilizzati durante la build, incluse quelli che hanno utilizzato lo "shared state".
- Visualizzare le relazioni di dipendenza tra ricette, pacchetti e task.
- Visualizzare informazioni sulle prestazioni, come tempo di compilazione, tempo di esecuzione dei task, utilizzo della CPU e I/O del disco.

Per una panoramica di Toaster, guardare questo [video introduttivo](#).


### 13.1.2 Opzioni di Installazione

È possibile configurare Toaster per l'esecuzione come istanza locale o come servizio condiviso [shared].

Quando Toaster è configurato come istanza locale, tutti i componenti risiedono su un singolo host di build. Fondamentalmente, un'istanza locale di Toaster è adatta a un singolo utente che sviluppa su un singolo host di build.



Toaster come servizio condiviso è adatto a più utenti che sviluppano su diversi host di build. Quando Toaster è configurato come servizio condiviso [shared], i suoi componenti possono essere distribuiti su più macchine:



## 13.2 Preparazione all'Uso di Toaster

Questo capitolo descrive come preparare il sistema per utilizzare Toaster.

### 13.2.1 Impostazione dei Requisiti di Sistema di Base

Prima di poter utilizzare Toaster, è necessario configurare il sistema di build per eseguire Yocto Project. Per fare ciò, seguire le istruzioni nella sezione "*Preparing the Build Host*" del Manuale di Sviluppo dei Task di Yocto Project. Per Ubuntu/Debian, potrebbe essere necessario installare anche pip3.

```
$ sudo apt install python3-pip
```

### 13.2.2 Impostazione delle Dipendenze di Sistema di Toaster

Toaster richiede dipendenze Python aggiuntive per funzionare. Un file di requisiti di Toaster denominato `toaster-requirements.txt` definisce le dipendenze Python. Il file di requisiti si trova nella directory `bitbake`, che si trova nella directory principale della *Source Directory* (ad esempio `poky/bitbake/toaster-requirements.txt`). Le dipendenze vengono visualizzate in un formato compatibile con `pip`.

#### Installare i Pacchetti di Toaster

È necessario installare i pacchetti richiesti da Toaster. Usare questo comando:

```
$ pip3 install --user -r bitbake/toaster-requirements.txt
```

Il comando precedente installa i moduli Toaster necessari in una cache locale di Python 3 nella directory `$HOME`. La cache si trova effettivamente in `$HOME/.local`. Per vedere quali pacchetti sono stati installati nella directory `$HOME`, eseguire il seguente comando:

```
$ pip3 list installed --local
```

Se si deve rimuovere qualcosa, il seguente comando funziona:

```
$ pip3 uninstall PackageNameToUninstall
```

## 13.3 Configurazione e Utilizzo di Toaster

### 13.3.1 Avvio di Toaster per lo Sviluppo Locale

Dopo aver configurato Yocto Project e installato le dipendenze di sistema di Toaster come descritto nel capitolo "*Preparazione all'Uso di Toaster*", è possibile avviare Toaster.

Accedere alla *Source Directory* del progetto (ad esempio, poky):

```
$ cd poky
```

Una volta in tale directory, eseguire lo script dell'ambiente di compilazione:

```
$ source oe-init-build-env
```

Successivamente, dalla *Build Directory* (ad esempio, poky/build), avviare Toaster con questo comando:

```
$ source toaster start
```

È ora possibile eseguire le build dalla riga di comando o tramite Toaster, come spiegato nella sezione "*Utilizzo dell'Interfaccia Web di Toaster*".

Per accedere all'interfaccia web di Toaster, aprire il browser di default e inserire quanto segue:

```
http://127.0.0.1:8000
```

### 13.3.2 Impostazione di Una Porta Diversa

Per default, Toaster si avvia sulla porta 8000. Si può utilizzare il parametro `WEBPORT` per impostare una porta diversa. Ad esempio, il seguente comando imposta la porta su "8400":

```
$ source toaster start webport=8400
```

### 13.3.3 Configurazione di Toaster Senza un Server Web

È possibile avviare un ambiente Toaster senza avviare il relativo server web. Questo è utile per i seguenti scopi:

- Acquisire le statistiche di una build da riga di comando nel database di Toaster per un'analisi successiva.
- Acquisire le statistiche di una build da riga di comando quando il server Toaster è già in esecuzione.
- Avere un'istanza del server web di Toaster che monitora e acquisisce più build da riga di comando, ognuna delle quali viene avviata nel proprio ambiente Toaster "noweb".

I seguenti comandi mostrano come avviare un ambiente Toaster senza avviare il relativo server web, eseguire operazioni con BitBake e quindi arrestare l'ambiente Toaster. Una volta completata la build, è possibile chiudere l'ambiente Toaster. Prima di chiuderlo, tuttavia, è consigliabile attendere qualche minuto per garantire il trasferimento completo delle statistiche di build di BitBake al database di Toaster. Se si dispone di un'istanza separata del server web di Toaster in esecuzione, è possibile monitorare l'avanzamento di questa build da riga di comando ed esaminare i risultati non appena vengono pubblicati:

```
$ source toaster start noweb
$ bitbake target
$ source toaster stop
```

### 13.3.4 Configurazione di Toaster Senza un Server di Build

È possibile avviare un ambiente Toaster con la funzione "New Projects" disabilitata. Questa opzione è utile per i seguenti scopi:

- Condividere i risultati delle build sul server web, impedendo al contempo ad altri di avviare build sul proprio host.
- Consentire che solo le build locali da riga di comando vengano acquisite nel database di Toaster.

Utilizzare il seguente comando per configurare Toaster senza un server di build:

```
$ source toaster start nobuild webport=port
```

### 13.3.5 Configurazione dell'Accesso Esterno

Per si associa all'indirizzo di loopback (ovvero `localhost`), che non consente l'accesso da host esterni. Per consentire l'accesso esterno, utilizzare il parametro `WEBPORT` per aprire un indirizzo che si connetta alla rete, in particolare l'indirizzo IP utilizzato dalla scheda di rete per connettersi alla rete. È anche possibile associarsi a tutti gli indirizzi IP supportati dal computer utilizzando la scorciatoia `"0.0.0.0:port"`.

L'esempio seguente si collega a tutti gli indirizzi IP dell'host:

```
$ source toaster start webport=0.0.0.0:8400
```

Questo esempio si collega a uno specifico indirizzo IP sulla scheda di rete dell'host:

```
$ source toaster start webport=192.168.1.1:8400
```

### 13.3.6 La Directory per la Clonazione dei Layer

Toaster crea una directory `_toaster_clones` all'interno della Source Directory (ad esempio `poky`) per clonare tutti i layer necessari per le build.

In alternativa, se si desidera che tutti i file e le directory relativi a Toaster si trovino in una posizione diversa da quella predefinita, è possibile impostare la variabile d'ambiente `TOASTER_DIR`, che ha la precedenza sulla directory di lavoro corrente. Impostando questa variabile d'ambiente, Toaster crea e utilizza `$TOASTER_DIR/_toaster_clones`.

### 13.3.7 La Build Directory

Toaster crea una *Build Directory* all'interno della Source Directory (ad esempio poky) per eseguire le build.

In alternativa, se si desidera che tutti i file e le directory relativi a Toaster si trovino in una posizione specifica, si può impostare la variabile d'ambiente `TOASTER_DIR`, che ha la precedenza sulla directory di lavoro corrente. Impostando questa variabile d'ambiente, Toaster utilizzerà `$TOASTER_DIR/build` come *Build Directory*.

### 13.3.8 Creazione di un Superutente Django

Toaster è basato sul framework Django. Django fornisce un'interfaccia di amministrazione utilizzabile per modificare i parametri di configurazione di Toaster.

Per accedere all'interfaccia di amministrazione di Django, si deve creare un superutente seguendo questi passaggi:

1. Se è stato usato `pip3`, come consigliato, per configurare le dipendenze di sistema di Toaster, il percorso dell'utente locale deve essere presente nell'elenco `PATH`. Per aggiungere il path dell'utente locale `pip3`, utilizzare il seguente comando:

```
$ export PATH=$PATH:$HOME/.local/bin
```

2. Dalla directory contenente il database di Toaster, che per default è *Build Directory*, richiamare il comando `createsuperuser` da `manage.py`:

```
$ cd poky/build
$ ../bitbake/lib/toaster/manage.py createsuperuser
```

3. Django richiederà il nome utente, che è necessario fornire.
4. Django richiederà un indirizzo email, che è facoltativo.
5. Django richiederà una password, che è obbligatoria.
6. Django richiederà di reinserire la password per la verifica.

Dopo aver completato questi passaggi, verrà visualizzato il seguente messaggio di conferma:

```
Superuser created successfully.
```

La creazione di un superutente consente di accedere all'interfaccia di amministrazione di Django tramite un browser. L'URL per questa interfaccia è lo stesso URL utilizzato per l'istanza di Toaster con `/admin` alla fine. Ad esempio, se si sta eseguendo Toaster in locale, si usa il seguente URL:

```
http://127.0.0.1:8000/admin
```

Si può usare l'interfaccia di amministrazione di Django per impostare i parametri di configurazione di Toaster, come la *Build Directory*, le sorgenti dei layer, i valori di default delle variabili e le versioni di BitBake.

### 13.3.9 Configurazione di un'Istanza di Produzione di Toaster

Si può usare un'istanza di produzione di Toaster per condividerla con utenti remoti, più utenti o entrambi. L'istanza di produzione è anche la configurazione in grado di gestire carichi di lavoro più elevati sul servizio web. Seguire le istruzioni nelle sezioni seguenti per configurare Toaster ed eseguire le build tramite l'interfaccia web di Toaster.

#### Requisiti

Assicurarsi di soddisfare i seguenti requisiti:

##### Nota

Si devono rispettare tutti i requisiti di Apache, `mod-wsgi` e Mysql.

- Si devono soddisfare tutti i requisiti di compilazione descritti nel capitolo "*Preparazione all'Uso di Toaster*".
- Si deve avere un server web Apache.
- Si deve avere `mod-wsgi` installato per il server web Apache.
- Utilizzare il server di database MySQL.
- Se si usa Ubuntu, eseguire il seguente comando:

```
$ sudo apt install apache2 libapache2-mod-wsgi-py3 mysql-server python3-pip_
↳ libmysqlclient-dev
```

- Se si usa Fedora o una distribuzione Red Hat, eseguire il seguente comando:

```
$ sudo dnf install httpd python3-mod_wsgi python3-pip mariadb-server mariadb-
↳ devel python3-devel
```

- Se si usa openSUSE, eseguire il seguente comando:

```
$ sudo zypper install apache2 apache2-mod_wsgi-python3 python3-pip mariadb_
↳ mariadb-client python3-devel
```

#### Installazione

Eseguire i seguenti passaggi per installare Toaster:

1. Crea l'utente toaster e impostare la sua directory home su `/var/www/toaster`:

```
$ sudo /usr/sbin/useradd toaster -md /var/www/toaster -s /bin/false
$ sudo su - toaster -s /bin/bash
```

2. Eseguire il checkout di una copia di poky nella directory del server web. Si userà la directory `/var/www/toaster`:

```
$ git clone https://git.yoctoproject.org/poky
$ git checkout blacksail
```

3. Installare le dipendenze di Toaster utilizzando il flag `--user`, che mantiene i pacchetti Python isolati dai pacchetti forniti dal proprio sistema:

```
$ cd /var/www/toaster/  
$ pip3 install --user -r ./poky/bitbake/toaster-requirements.txt  
$ pip3 install --user mysqlclient
```

**i Nota**

Isolare questi pacchetti non è obbligatorio, ma è consigliato. In alternativa, si può utilizzare il gestore di pacchetti del sistema operativo per installare i pacchetti.

4. Configurare Toaster modificando il file `/var/www/toaster/poky/bitbake/lib/toaster/toastermain/settings.py` come segue:

- Modificare le impostazioni di **DATABASES**:

```
DATABASES = {  
    'default': {  
        'ENGINE': 'django.db.backends.mysql',  
        'NAME': 'toaster_data',  
        'USER': 'toaster',  
        'PASSWORD': 'yourpasswordhere',  
        'HOST': 'localhost',  
        'PORT': '3306',  
    }  
}
```

- Modifica le impostazioni di **SECRET\_KEY**:

```
SECRET_KEY = 'your_secret_key'
```

- Modifica le impostazioni di **STATIC\_ROOT** <[https://docs.djangoproject.com/en/2.2/ref/settings/#std:setting-STATIC\\_ROOT](https://docs.djangoproject.com/en/2.2/ref/settings/#std:setting-STATIC_ROOT)>`\_\_`:

```
STATIC_ROOT = '/var/www/toaster/static_files/'
```

5. Aggiungere il database e l'utente al server mysql definito in precedenza:

```
$ mysql -u root -p  
mysql> CREATE DATABASE toaster_data;  
mysql> CREATE USER 'toaster'@'localhost' identified by 'yourpasswordhere';  
mysql> GRANT all on toaster_data.* to 'toaster'@'localhost';  
mysql> quit
```

6. Fare in modo che Toaster crei lo schema del database, i dati di default e raccolga i file statici:



```
$ cd /var/www/toaster/poky/
$ ./bitbake/lib/toaster/manage.py migrate
$ TOASTER_DIR=`pwd` TEMPLATECONF='poky' \
  ./bitbake/lib/toaster/manage.py checksettings
$ ./bitbake/lib/toaster/manage.py collectstatic
```

Nell'esempio precedente, dalla directory `poky`, il comando `migrate` garantisce che le modifiche allo schema del database siano state propagate correttamente (ovvero, esegue le migrazioni). La riga successiva imposta la directory radice di Toaster `TOASTER_DIR` e la posizione del file di configurazione di Toaster `TOASTER_CONF`, che è relativa a `TOASTER_DIR`. Il valore di `TEMPLATECONF` riflette il contenuto di `poky/.templateconf` e, per default, dovrebbe includere la stringa "poky". Per ulteriori informazioni sul file di configurazione di Toaster, consultare la sezione "[Configurazione di Toaster](#)".

Questa riga esegue anche il comando `checksettings`, che configura la posizione della *Build Directory* di Toaster. La directory radice di Toaster `TOASTER_DIR` determina dove viene creata la directory di build di Toaster sul file system. Nell'esempio precedente, `TOASTER_DIR` è impostato come segue:

```
/var/www/toaster/poky
```

Questa impostazione determina che la *Build Directory* di Toaster sia:

```
/var/www/toaster/poky/build
```

Infine, il comando `collectstatic` è un comando del framework Django che raccoglie tutti i file serviti staticamente in una directory designata per essere serviti dal server web Apache, come definito da `STATIC_ROOT`.

7. Testare e/o utilizzare l'integrazione MySQL con il server web Django di Toaster. A questo punto, si può avviare il normale server web Django di Toaster con il database di Toaster in MySQL. Si può utilizzare questo server web per verificare che la migrazione del database e il popolamento dei dati dall'indice del layer siano completi.

Per avviare il server web Toaster Django di default con il database Toaster ora in MySQL, si usano i comandi di avvio standard:

```
$ source oe-init-build-env
$ source toaster start
```

Inoltre, se Django è sufficiente per le proprie esigenze, lo si può usare come sistema di rilascio e migrare ad Apache in seguito, quando le esigenze cambieranno.

8. Aggiungere un file di configurazione Apache per Toaster alla directory di configurazione del server web Apache. Se si usa Ubuntu o Debian, si inserisce il file qui:

```
/etc/apache2/conf-available/toaster.conf
```

Se si usa Fedora o Red Hat, lo si inserisce qui:

```
/etc/httpd/conf.d/toaster.conf
```

Se si usa openSUSE, lo si inserisce qui:

```
/etc/apache2/conf.d/toaster.conf
```

Ecco un esempio di configurazione Apache per Toaster che si può seguire:

```
Alias /static /var/www/toaster/static_files
<Directory /var/www/toaster/static_files>
    <IfModule mod_access_compat.c>
        Order allow,deny
        Allow from all
    </IfModule>
    <IfModule !mod_access_compat.c>
        Require all granted
    </IfModule>
</Directory>

<Directory /var/www/toaster/poky/bitbake/lib/toaster/toastermain>
    <Files "wsgi.py">
        Require all granted
    </Files>
</Directory>

WSGIDaemonProcess toaster_wsgi python-path=/var/www/toaster/poky/bitbake/lib/
↳toaster:/var/www/toaster/.local/lib/python3.4/site-packages
WSGIScriptAlias / "/var/www/toaster/poky/bitbake/lib/toaster/toastermain/wsgi.
↳py"
<Location />
    WSGIProcessGroup toaster_wsgi
</Location>
```

Se si usa Ubuntu o Debian, si dovrà abilitare la configurazione e il modulo per Apache:

```
$ sudo a2enmod wsgi
$ sudo a2enconf toaster
$ chmod +x bitbake/lib/toaster/toastermain/wsgi.py
```

Infine, riavviare Apache per assicurarsi che tutta la nuova configurazione sia stata caricata. Per Ubuntu, Debian e openSUSE usare:

```
$ sudo service apache2 restart
```

Per Fedora e Red Hat si usa:

```
$ sudo service httpd restart
```

9. Preparare il servizio systemd per eseguire le build di Toaster. Ecco un esempio di file di configurazione per il servizio:

```
[Unit]
Description=Toaster runbuilds

[Service]
Type=forking User=toaster
ExecStart=/usr/bin/screen -d -m -S runbuilds /var/www/toaster/poky/bitbake/lib/
↳toaster/runbuilds-service.sh start
ExecStop=/usr/bin/screen -S runbuilds -X quit
WorkingDirectory=/var/www/toaster/poky

[Install]
WantedBy=multi-user.target
```

Preparare lo script `runbuilds-service.sh` da posizionare nella directory `/var/www/toaster/poky/bitbake/lib/toaster/` impostando i permessi di esecuzione:

```
#!/bin/bash

#export http_proxy=http://proxy.host.com:8080
#export https_proxy=http://proxy.host.com:8080
#export GIT_PROXY_COMMAND=$HOME/bin/gitproxy
cd poky/
source ./oe-init-build-env build
source ../bitbake/bin/toaster $1 noweb
[ "$1" == 'start' ] && /bin/bash
```

10. Avviare il servizio:

```
$ sudo service runbuilds start
```

Poiché il servizio è in esecuzione in una sessione screen distaccata, ci si può connettere ad esso utilizzando questo comando:

```
$ sudo su - toaster
$ screen -rS runbuilds
```

Vi si può disconnettere dal servizio utilizzando la combinazione di tasti "Ctrl-a" seguita da "d".

Ora si può aprire un browser e iniziare a usare Toaster.

### 13.3.10 Utilizzo dell'Interfaccia Web di Toaster

L'interfaccia web di Toaster consente di eseguire le seguenti operazioni:

- Esplorare i layer pubblicati nell'[OpenEmbedded Layer Index](#) disponibili per la versione del sistema di build selezionata.
- Importare i propri layer per la compilazione.
- Aggiungere e rimuovere layer dalla configurazione.
- Impostare le variabili di configurazione.
- Selezionare uno o più target da compilare.
- Avviare le build.
- Visualizzare cosa è stato compilato (ricette e pacchetti) e quali pacchetti sono stati installati nell'immagine finale.
- Esplorare la struttura delle directory dell'immagine.
- Visualizzare il valore di tutte le variabili nella configurazione di build e quali file impostano ciascun valore.
- Esaminare i messaggi di errore, warning e trace [traccia] per facilitare il debug.
- Visualizzare informazioni sui task di BitBake eseguiti e riutilizzati durante la build, incluse quelli che hanno utilizzato lo "shared state".
- Visualizzare le relazioni di dipendenza tra ricette, pacchetti e task.
- Visualizzare informazioni sulle prestazioni, come tempo di compilazione, tempo di esecuzione dei task, utilizzo della CPU e I/O del disco.

#### Video sull'Interfaccia Web di Toaster

Ecco alcuni video che mostrano come utilizzare l'interfaccia grafica di Toaster:


- *Build Configuration:* Questo [video](#) offre una panoramica e una dimostrazione della configurazione della build per Toaster.
- *Build Custom Layers:* Questo [video](#) mostra come creare layer personalizzati da utilizzare con Toaster.
- *Toaster Homepage and Table Controls:* Questo [video](#) illustra la pagina di inserimento di Toaster e fornisce una panoramica delle funzionalità di manipolazione dei dati di Toaster, che includono ricerca, ordinamento e filtraggio in base a diversi criteri.
- *Build Dashboard:* Questo [video](#) mostra la dashboard di build, una pagina che fornisce una panoramica delle informazioni disponibili per una build selezionata.
- *Image Information:* Questo [video](#) illustra le informazioni fornite da Toaster sulle immagini: pacchetti installati e file system root.
- *Configuration:* Questo [video](#) fornisce informazioni sulla configurazione di build di Toaster.
- *Tasks:* Questo [video](#) mostra le informazioni fornite da Toaster sui task eseguiti dal sistema di build.
- *Recipes and Packages Built:* Questo [video](#) mostra le informazioni fornite da Toaster sulle ricette e sui pacchetti creati.

- *Performance Data*: Questo [video](#) mostra i dati sulle prestazioni di build forniti da Toaster.

## Ulteriori Informazioni sulla Release di Yocto Project Locale

Questa sezione si applica solo se è stato configurato Toaster per lo sviluppo locale, come spiegato nella sezione "[Avvio di Toaster per lo Sviluppo Locale](#)".

Quando si crea un progetto in Toaster, verrà chiesto di fornire un nome e di selezionare una release di Yocto Project. Una delle opzioni di release che si troverà si chiama "Local Yocto Project".



Quando si seleziona la release "Local Yocto Project", Toaster eseguirà le build utilizzando la copia locale di Yocto Project presente sul proprio computer: la stessa copia che si usa per eseguire Toaster. A meno che non si aggiorni manualmente questa copia, le build utilizzeranno sempre la stessa revisione Git.

Se si seleziona una qualsiasi delle altre opzioni di release, Toaster scaricherà l'ultima versione della release selezionata dal repository upstream [Yocto Project repository](#) ogni volta che si esegue una build. Scaricare questa ultima versione significa che, se la release selezionata viene aggiornata a monte, la revisione Git utilizzata per le build cambierà. Se si sta sviluppando in locale, si potrebbe non volere che ciò accada. In tal caso, la release "Local Yocto Project" potrebbe essere la scelta giusta.

Tuttavia, la versione "Local Yocto Project" non include layer compatibili, ad eccezione dei tre layer principali forniti con Yocto Project:

- [openembedded-core](#)
- [meta-poky](#)
- [meta-yocto-bsp](#)

The screenshot shows the Yocto Project Toaster web interface. The top navigation bar includes the 'yocto PROJECT' logo, 'Toaster' title, and links for 'All builds' and 'All projects'. There are buttons for 'New project' and 'Manual'. The main content area is titled 'My project' and has tabs for 'Configuration', 'Builds (0)', 'Import layer', and 'New custom image'. A search bar with the placeholder 'Type the recipe you want to build' and a 'Build' button is present. The left sidebar contains a 'Configuration' section with links for 'Compatible metadata', 'Custom images', 'Image recipes', 'Software recipes', 'Machines', and 'Layers' (which is highlighted). Below this is an 'EXTRA CONFIGURATION' section with a link for 'BitBake variables'. The main content area is titled 'Compatible layers (3)' and features a search bar, 'Edit columns' button, and 'Show rows: 25' dropdown. A table lists three compatible layers:

| Layer             | Summary       | Git revision | Dependencies | Add   Remove |
|-------------------|---------------|--------------|--------------|--------------|
| meta-poky         |               | HEAD         |              | Remove layer |
| meta-yocto-bsp    |               | HEAD         |              | Remove layer |
| openembedded-core | Core metadata | HEAD         |              | Remove layer |

A 'Show rows: 25' dropdown is located at the bottom right of the table.

Per creare altri layer, sarà necessario importarli manualmente nel progetto Toaster utilizzando la pagina "Import layer".

yocto PROJECT Toaster ⓘ All builds All projects New project Manual

## My project

Configuration Builds (0) **Import layer** New custom image

⊙ Type the recipe you want to build **Build**

### Layer repository information

The layer you are importing must be compatible with **Local Yocto Project**, which is the release you are using in this project.

Layer name ⓘ

Git repository URL ⓘ

Repository subdirectory (optional) ⓘ

Git revision ⓘ

### Layer dependencies (optional) ⓘ

openembedded-core

Type a layer name  **Add layer** You can only add layers Toaster knows about

**Import and add to project** To import a layer you need to enter a layer name, a Git repository URL and a revision (branch, tag or commit)

### Building di una Ricetta Specifica con più Versioni

Occasionalmente, un layer potrebbe fornire più di una versione della stessa ricetta. Ad esempio, il layer `openembedded-core` fornisce due versioni della ricetta `bash` (ovvero 3.2.48 e 4.3.30-r0) e due versioni della ricetta `which` (ovvero 2.21 e 2.18). La figura seguente mostra esattamente questo scenario:

yocto  
PROJECT
Toaster ⓘ
All builds
All projects
New build ▼
New project
Manual

Demo project: Configuration → Compatible layers → openembedded-core (master)

## openembedded-core (master)

Layer details
Recipes (4)
Machines (7)

Delete the openembedded-core layer from your project

bash
x Search
Show rows: 25 ▼

| Recipe ▼ | Description                                                                                                                                                                                                                       | Version   | Build recipe |
|----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|--------------|
| bash     | An sh-compatible command language interpreter                                                                                                                                                                                     | 3.2.48    | Build recipe |
| bash     | An sh-compatible command language interpreter.                                                                                                                                                                                    | 4.3.30-r0 | Build recipe |
| which    | Which is a utility that prints out the full path of the executables that bash(1) would execute when the passed program names would have been entered on the shell prompt. It does this by using the exact same algorithm as bash. | 2.21      | Build recipe |
| which    | Which is a utility that prints out the full path of the executables that bash(1) would execute when the passed program names would have been entered on the shell prompt. It does this by using the exact same algorithm as bash. | 2.18      | Build recipe |

Show rows: 25 ▼

### About openembedded-core

**Summary** ⓘ  
Core metadata

**Description**  
OpenEmbedded-Core is a layer containing the core metadata for current versions of OpenEmbedded. It is distro-less (can build a functional image with DISTRO = "") and contains only emulated machine support.

Per default, il sistema di build di OpenEmbedded compila una delle due ricette. Nel caso di `bash`, viene compilata di default la versione 4.3.30-r0. Sfortunatamente, Toaster, nella sua configurazione attuale, non è in grado di sovrascrivere la versione predefinita della ricetta. Per compilare `bash` 3.2.48, è necessario impostare la variabile `PREFERRED_VERSION`. È possibile farlo da Toaster, utilizzando il modulo "Add variable", disponibile nella pagina "BitBake variables" della sezione di configurazione del progetto, come mostrato nella schermata seguente:



## Demo project

Builds (1) **Configuration** Import layer

 **Build**

### Configuration

COMPATIBLE METADATA

Image recipes

Software recipes

Machines

Layers

EXTRA CONFIGURATION

**BitBake variables**

### Bitbake variables

**DISTRO** ⓘpoky **IMAGE\_FSTYPES** ⓘext3 jffs2 tar.bz2 **IMAGE\_INSTALL\_append** ⓘNot set **PACKAGE\_CLASSES** ⓘpackage\_rpm **SDKMACHINE** ⓘx86\_64 

#### Add variable

Variable ⓘ

Value

**Add variable**

#### Some variables are reserved from Toaster

Toaster cannot set any variables that impact 1) the configuration of the build servers, or 2) where artifacts produced by the build are stored. Such variables include:

[BB\\_DISKMON\\_DIRS](#)
[BB\\_NUMBER\\_THREADS](#)
[CVS\\_PROXY\\_HOST](#)  
[CVS\\_PROXY\\_PORT](#)
[DL\\_DIR](#)
[PARALLEL\\_MAKE](#)
[SSTATE\\_DIR](#)  
[SSTATE\\_MIRRORS](#)
[TMPDIR](#)

Plus the following standard shell environment variables:

[http\\_proxy](#)
[ftp\\_proxy](#)
[https\\_proxy](#)
[all\\_proxy](#)

Per specificare `bash 3.2.48` come versione da compilare, inserire `"PREFERRED_VERSION_bash"` nel campo "Variable" e `"3.2.48"` nel campo "Value". Quindi, cliccare sul pulsante "Add variable":

yocto  
PROJECT

Toaster ⓘ

All builds

All projects

New project

Manual

## Demo project

Builds (1)

Configuration

Import layer

Type the recipe you want to build

Build

Configuration

COMPATIBLE METADATA

Image recipes

Software recipes

Machines

Layers

EXTRA CONFIGURATION

BitBake variables

### Bitbake variables

**DISTRO** ⓘ  
poky 

**IMAGE\_FSTYPES** ⓘ  
ext3 jffs2 tar.bz2 

**IMAGE\_INSTALL\_append** ⓘ  
Not set 

**PACKAGE\_CLASSES** ⓘ  
package\_rpm 

**SDKMACHINE** ⓘ  
x86\_64 

**Add variable**

Variable ⓘ  
PREFERRED\_VERSION\_bash

Value  
3.2.48

Add variable

**Some variables are reserved from Toaster**  
Toaster cannot set any variables that impact 1) the configuration of the build servers, or 2) where artifacts produced by the build are stored. Such variables include:  
[BB\\_DISKMON\\_DIRS](#) [BB\\_NUMBER\\_THREADS](#) [CVS\\_PROXY\\_HOST](#)  
[CVS\\_PROXY\\_PORT](#) [DL\\_DIR](#) [PARALLEL\\_MAKE](#) [SSTATE\\_DIR](#)  
[SSTATE\\_MIRRORS](#) [TMPDIR](#)  
Plus the following standard shell environment variables:  
[http\\_proxy](#) [ftp\\_proxy](#) [https\\_proxy](#) [all\\_proxy](#)

Dopo aver cliccato sul pulsante "Add variable", le impostazioni per `PREFERRED_VERSION` vengono aggiunte in fondo all'elenco delle variabili BitBake. Con queste impostazioni, il sistema di build OpenEmbedded compila la versione desiderata della ricetta anziché la versione di default:

yocto

PROJECT

Toaster

All builds

All projects

New project

Manual

Demo project

Builds (1)

Configuration

Import layer

Type the recipe you want to build

Build

Configuration

COMPATIBLE METADATA

Recipes

Machines

Layers

EXTRA CONFIGURATION

BitBake variables

Bitbake variables

DISTRO

poky

IMAGE\_FSTYPES

ext3 jffs2 tar.bz2

IMAGE\_INSTALL\_append

Not set

PACKAGE\_CLASSES

package\_rpm

SDKMACHINE

x86\_64

PREFERRED\_VERSION\_bash

3.2.48

Add variable

Variable

Type variable name

Value

Type variable value

Add variable

Some variables are reserved from Toaster

Toaster cannot set any variables that impact 1) the configuration of the build servers, or 2) where artifacts produced by the build are stored. Such variables include:

BB\_DISKMON\_DIRS BB\_NUMBER\_THREADS CVS\_PROXY\_HOST CVS\_PROXY\_PORT DL\_DIR PARALLEL\_MAKE SSTATE\_DIR SSTATE\_MIRRORS TMPDIR

Plus the following standard shell environment variables:

http\_proxy ftp\_proxy https\_proxy all\_proxy

## 13.4 Concetti e Riferimenti

Per configurare e utilizzare Toaster, è necessario comprendere alcuni concetti e disporre di un riferimento di base sui comandi. Questo capitolo finale fornisce informazioni concettuali sui sorgenti dei layer, le release e i file di configurazione JSON. Viene inoltre fornita una rapida panoramica di alcuni utili comandi `manage.py` specifici di Toaster. Informazioni sui comandi `manage.py` sono disponibili sul Web e questo manuale non intende in alcun modo fornire un riferimento completo dei comandi.

### 13.4.1 Sorgenti dei Layer

In generale, una "sorgente di layer" è una fonte di informazioni sui layer esistenti. In particolare, ci occupiamo dei layer utilizzabili con Yocto Project e Toaster. Questo capitolo descrive un tipo specifico di sorgente di layer, chiamato "layer index" [indice di layer].

Un indice di layer è un'applicazione web che contiene informazioni su un insieme di layer personalizzati. Un buon esempio di indice di layer esistente è l'OpenEmbedded Layer Index. Un'istanza pubblica di questo indice di layer è disponibile all'indirizzo <https://layers.openembedded.org/>. Il codice sorgente dell'applicazione web di questo indice di layer è disponibile all'indirizzo <https://git.yoctoproject.org/layerindex-web/>.

Quando si collega una sorgente di layer a Toaster, quest'ultimo può interrogare la sorgente tramite un'API [REST](#), memorizzare le informazioni sui layer nel database di Toaster e quindi mostrare tali informazioni agli utenti. Gli utenti possono quindi visualizzare queste informazioni e creare layer direttamente da Toaster senza dover clonare o modificare il file di configurazione dei layer di BitBake [build/conf/bblayers.conf](#).

Integrare una sorgente di layer in Toaster è utile quando si hanno molti layer personalizzati che devono essere creati regolarmente da una community di sviluppatori. Infatti, Toaster è preconfigurato con l'OpenEmbedded Metadata Index.

**Nota**

Non è obbligatorio utilizzare una sorgente di layer per usare Toaster. L'integrazione con una sorgente di layer è facoltativa.

## Configurazione e Utilizzo di una Sorgente di Layer

Per utilizzare la propria sorgente di layer, è necessario configurarla e quindi integrarla in Toaster. Questa sezione descrive come integrarsi con un indice di layer in modo simile a come Toaster si integra con l'OpenEmbedded Metadata Index.

## Comprensione dei Layer

Il primo passo ovvio per utilizzare un indice di layer è quello di avere diversi layer personalizzati che gli sviluppatori creano e a cui accedono regolarmente tramite Yocto Project. Questo set di layer deve esistere ed è necessario sapere dove si trovano. Queste informazioni saranno necessarie quando si configura il codice per l'applicazione web che si "aggancia" al set di layer.

Per informazioni generali sui layer, consultare la sezione "[Il Modello a Layer di Yocto Project](#)" nella Manuale Introdotivo e Concetti di Yocto Project. Per informazioni su come creare layer, consultare la sezione "[Comprendere e Creare i Layer](#)" nel Manuale di Sviluppo dei Task di Yocto Project.

## Configurazione di Toaster per Agganciarsi al Proprio Indice di Layer

Affinché Toaster utilizzi il proprio indice di layer, si deve ospitare l'applicazione web su un server a cui Toaster possa connettersi. Si devono anche fornire a Toaster le informazioni sull'indice di layer. In altre parole, è necessario configurare Toaster per utilizzare il proprio indice di layer. Questa sezione descrive due metodi per configurare e utilizzare l'indice di layer.

Nella sezione precedente, è stato fatto riferimento al codice dell'Indice di Metadati OpenEmbedded (ovvero <https://layers.openembedded.org/>) È possibile utilizzare questo codice, che si trova in <https://git.yoctoproject.org/layerindex-web/>, come base per creare il proprio indice di layer.

## Utilizzare l'Interfaccia di Amministrazione

Accedere all'interfaccia di amministrazione tramite un browser inserendo l'URL dell'istanza di Toaster e aggiungendo `/admin` alla fine dell'URL. Ad esempio, se si esegue Toaster in locale, utilizzare il seguente URL:

```
http://127.0.0.1:8000/admin
```

L'interfaccia di amministrazione presenta una sezione "Layer sources" che include un pulsante "Add layer source". Cliccare su questo pulsante e fornire le informazioni richieste. Assicurarsi di selezionare "layerindex" come tipo di origine layer.

### Utilizzo della Funzionalità Fixture

La funzionalità Fixture di Django sovrascrive il server di layer di default quando la si utilizza per specificare un URL personalizzato. Per utilizzare la funzionalità Fixture, creare (o modificare) il file `bitbake/lib/toaster.orm/fixtures/custom.xml` e impostare la seguente configurazione di Toaster col proprio URL personalizzato:

```
<?xml version="1.0" ?>
<django-objects version="1.0">
  <object model="orm.toastersetting" pk="100">
    <field name="name" type="CharField">CUSTOM_LAYERINDEX_SERVER</field>
    <field name="value" type="CharField">https://layers.my_organization.org/
    ↳layerindex/branch/master/layers/</field>
  </object>
</django-objects>
```

Quando si avvia Toaster per la prima volta, o se si elimina il file `toaster.sqlite` e lo si riavvia, il database verrà popolato correttamente da questo server di indice dei layer.

Una volta aggiornate le informazioni, verificare che le nuove informazioni sui layer siano disponibili utilizzando l'interfaccia web di Toaster. Per farlo, visitare la pagina "All compatible layers" all'interno di un progetto Toaster. I layer della propria sorgente di layer dovrebbero essere elencati lì.

Se si modificano le informazioni nel server di indice dei layer, aggiornare il database di Toaster eseguendo il seguente comando:

```
$ bitbake/lib/toaster/manage.py lsupdates
```

Se Toaster riesce a raggiungere l'URL dell'API, verrà visualizzato un messaggio che informa che Toaster sta aggiornando le informazioni della sorgente dei layer.

### 13.4.2 Release

Quando si crea un progetto Toaster tramite l'interfaccia web, viene richiesto di scegliere una "Release". Nel contesto di Toaster, il termine "Release" si riferisce a un insieme di layer e a una versione di BitBake utilizzati dal sistema di build OpenEmbedded per la compilazione. Toaster è preconfigurato con release corrispondenti ai branch di rilascio di Yocto Project. Tuttavia, è possibile modificare, eliminare e creare nuove release in base alle proprie esigenze. Questa sezione fornisce alcune informazioni di base sulle release.

## Release Pre-Configure

Toaster è configurato per utilizzare un set specifico di release. Naturalmente, è sempre possibile configurare Toaster per utilizzare qualsiasi release. Ad esempio, si potrebbe voler compilare il progetto con una specifica commit di una qualsiasi delle release predefinite. Oppure, si potrebbe voler compilare il progetto con diverse revisioni di OpenEmbedded e BitBake.

Nella configurazione di default, Toaster è compatibile con le seguenti versioni:

- *Yocto Project 6.1 "Blacksail" o OpenEmbedded "Blacksail"*: Questa versione fa sì che i progetti Toaster vengano compilati utilizzando l'ultima versione del branch blacksail, disponibile all'indirizzo <https://git.yoctoproject.org/poky/log/?h=blacksail> o <https://git.openembedded.org/openembedded-core/commit/?h=blacksail>.
- *Yocto Project "Master" o OpenEmbedded "Master"*: Questa versione fa sì che i progetti Toaster vengano compilati utilizzando l'ultima versione del branch master, dove si svolge lo sviluppo attivo, disponibile all'indirizzo <https://git.yoctoproject.org/poky/log/> o <https://git.openembedded.org/openembedded-core/log/>.
- *Local Yocto Project o Local OpenEmbedded*: Questa versione fa sì che i progetti Toaster vengano compilati utilizzando la versione più recente del clone di poky o openembedded-core che si ha in locale sulla macchina su cui è in esecuzione Toaster.

## 13.4.3 Configurazione di Toaster

Per utilizzare Toaster, è necessario configurare il database con i contenuti di default. Le seguenti sottosezioni descrivono vari aspetti della configurazione di Toaster.

### Configurazione del Flusso di Lavoro

Il file `bldcontrol/management/commands/checksettings.py` controlla la configurazione del workflow [flusso di lavoro]. Ecco la procedura per popolare inizialmente questo database.

1. Le impostazioni di default del progetto vengono definite dal file `orm/fixtures/settings.xml`.
2. La distribuzione e i layer di default del progetto vengono aggiunti dal file `orm/fixtures/poky.xml` se Poky è installato. Se Poky non è installato, vengono aggiunti dal file `orm/fixtures/oe-core.xml`.
3. Se il file `orm/fixtures/custom.xml` esiste, i suoi valori vengono aggiunti.
4. L'indice dei layer viene quindi scansionato e aggiunto al database.

Una volta completati questi passaggi, Toaster è configurato e pronto per l'uso.

### Personalizzazione dei Dati Pre-Impostati

I dati preimpostati per Toaster sono facilmente personalizzabili. È possibile creare il file `orm/fixtures/custom.xml` per personalizzare i valori inseriti nel database. La personalizzazione è additiva e può estendere o sostituire completamente i valori esistenti.

Il file `orm/fixtures/custom.xml` viene utilizzato per modificare le impostazioni di default del progetto per la macchina, la distribuzione, le immagini dei file e i layer. Quando si crea un nuovo progetto, è possibile utilizzare il file per definire le opzioni alternative di rilascio del progetto. Ad esempio, è possibile aggiungere una o più opzioni aggiuntive che presentano set di layer o distribuzioni personalizzati e qualsiasi altro contenuto locale o proprietario.

Inoltre, è possibile disabilitare completamente il contenuto dei file `oe-core.xml` e `poky.xml` definendo la sezione mostrata di seguito nel file `settings.xml`. Ad esempio, questa opzione è particolarmente utile se la configurazione personalizzata definisce un numero inferiore di release o layer rispetto ai file di fixture di default.

L'esempio seguente imposta "name" a "CUSTOM\_XML\_ONLY" e il suo valore su "True".

```
<object model="orm.toastersetting" pk="99">
  <field type="CharField" name="name">CUSTOM_XML_ONLY</field>
  <field type="CharField" name="value">True</field>
</object>
```

## Comprensione del Formato dei File di Fixture

Ecco una panoramica del formato dei file utilizzati da `oe-core.xml`, `poky.xml` e `custom.xml`.

Le seguenti sottosezioni descrivono ciascuna sezione dei file di fixture e forniscono un esempio di sezione del codice XML utilizzabile per comprendere queste informazioni e creare un file `custom.xml` locale.

### Definizione della Distribuzione di Default e di Altri Valori

Questa sezione definisce il valore di default della distribuzione per i nuovi progetti. Per default, riserva il primo record di Toaster Setting "1". Di seguito viene mostrato come impostare il valore di default del progetto per *DISTRO*:

```
<!-- Set the project default value for DISTRO -->
<object model="orm.toastersetting" pk="1">
  <field type="CharField" name="name">DEFCONF_DISTRO</field>
  <field type="CharField" name="value">poky</field>
</object>
```

È possibile sovrascrivere altri valori di default del progetto aggiungendo ulteriori sezioni di Toaster Setting, come ad esempio le impostazioni provenienti dal file `settings.xml`. È inoltre possibile aggiungere valori personalizzati inclusi nell'ambiente BitBake. I valori "pk" devono essere univoci. Per convenzione, i valori che definiscono i valori predefiniti del progetto hanno il prefisso "DEFCONF".

### Definizione della Versione di BitBake

Quanto segue definisce la versione di BitBake utilizzata per la successiva selezione della release:

```
<!-- Bitbake versions which correspond to the metadata release -->
<object model="orm.bitbakeversion" pk="1">
  <field type="CharField" name="name">blacksail</field>
  <field type="CharField" name="giturl">https://git.yoctoproject.org/poky</field>
  <field type="CharField" name="branch">blacksail</field>
  <field type="CharField" name="dirpath">bitbake</field>
</object>
```

## Definizione della Release

Quanto segue definisce le release quando si crea un nuovo progetto:

```
<!-- Releases available -->
<object model="orm.release" pk="1">
  <field type="CharField" name="name">blacksail</field>
  <field type="CharField" name="description">Yocto Project 6.1 "Blacksail"</field>
  <field rel="ManyToOneRel" to="orm.bitbakeversion" name="bitbake_version">1</
  <field>
  <field type="CharField" name="branch_name">blacksail</field>
  <field type="TextField" name="helptext">Toaster will run your builds using the
  <tip of the <a href="https://git.yoctoproject.org/cgit/cgit.cgi/poky/log/?
  <h=blacksail">Yocto Project Blacksail branch</a>.</field>
</object>
```

Il valore "pk" deve corrispondere alla rispettiva versione di BitBake indicata sopra.

## Definizione dei Nomi dei Layer di Default per la Release

Quanto segue definisce i layer di default per ciascuna release:

```
<!-- Default project layers for each release -->
<object model="orm.releasedefaultlayer" pk="1">
  <field rel="ManyToOneRel" to="orm.release" name="release">1</field>
  <field type="CharField" name="layer_name">openembedded-core</field>
</object>
```

I valori 'pk' nell'esempio precedente devono iniziare da "1" e incrementare in modo univoco. È possibile utilizzare lo stesso nome di layer in più release.

## Definizione delle Definizioni dei Layer

Le definizioni dei layer sono le più complesse. Quanto segue definisce ciascun layer e quindi specifica la versione esatta del layer utilizzata per ogni rispettiva release. È necessario avere una voce `orm.layer` per ogni layer. Quindi, per ogni voce è necessario un set di voci `orm.layer_version` che colleghino il layer a ogni release che lo include. In generale, tutte le release includono il layer.

```
<object model="orm.layer" pk="1">
  <field type="CharField" name="name">openembedded-core</field>
  <field type="CharField" name="layer_index_url"></field>
  <field type="CharField" name="vcs_url">https://git.yoctoproject.org/poky</field>
  <field type="CharField" name="vcs_web_url">https://git.yoctoproject.org/cgit/
  <cggit.cgi/poky</field>
  <field type="CharField" name="vcs_web_tree_base_url">https://git.yoctoproject.
  <org/cgit/cgit.cgi/poky/tree/%path%?h=%branch%</field>
```

(continues on next page)



(continua dalla pagina precedente)

```

    <field type="CharField" name="vcs_web_file_base_url">https://git.yoctoproject.
    ↪org/cgit/cgit.cgi/poky/tree/%path%?h=%branch%</field>
</object>
<object model="orm.layer_version" pk="1">
    <field rel="ManyToOneRel" to="orm.layer" name="layer">1</field>
    <field type="IntegerField" name="layer_source">0</field>
    <field rel="ManyToOneRel" to="orm.release" name="release">1</field>
    <field type="CharField" name="branch">blacksail</field>
    <field type="CharField" name="dirpath">meta</field>
</object> <object model="orm.layer_version" pk="2">
    <field rel="ManyToOneRel" to="orm.layer" name="layer">1</field>
    <field type="IntegerField" name="layer_source">0</field>
    <field rel="ManyToOneRel" to="orm.release" name="release">2</field>
    <field type="CharField" name="branch">HEAD</field>
    <field type="CharField" name="commit">HEAD</field>
    <field type="CharField" name="dirpath">meta</field>
</object>
<object model="orm.layer_version" pk="3">
    <field rel="ManyToOneRel" to="orm.layer" name="layer">1</field>
    <field type="IntegerField" name="layer_source">0</field>
    <field rel="ManyToOneRel" to="orm.release" name="release">3</field>
    <field type="CharField" name="branch">master</field>
    <field type="CharField" name="dirpath">meta</field>
</object>

```

I valori "pk" del layer sopra indicati devono essere univoci e in genere iniziano da "1". Anche i valori "pk" della versione del layer devono essere univoci per tutti i layer e in genere iniziano da "1".

### 13.4.4 Monitoraggio Remoto di Toaster

Toaster dispone di un'API che consente alle applicazioni di gestione remota di interrogare direttamente lo stato del server Toaster e delle sue build in modalità machine-to-machine. Questa API utilizza l'interfaccia [REST](#) e il trasferimento di file JSON. Ad esempio, è possibile monitorare una build all'interno di un container tramite porte HTTP note e supportate per accedere facilmente a un server Toaster all'interno del container. In questo esempio, utilizzando questa API JSON diretta, si evita di dover analizzare la pagina web rispetto alla visualizzazione mostrata all'utente.

#### Verifica dello Stato di Salute

Prima di utilizzare il monitoraggio remoto di Toaster, è consigliabile eseguire una verifica dello stato di salute. Per farlo, si esegue un ping al server Toaster utilizzando la seguente chiamata per verificare se è ancora attivo:

```
http://host:port/health
```

Assicurarsi di specificare host e porta. Se il server è attivo, si riceverà la seguente risposta HTML:

```
<!DOCTYPE html>
<html lang="en">
  <head><title>Toaster Health</title></head>
  <body>Ok</body>
</html>
```

## Determinare lo Stato delle Build in Corso

A volte è utile determinare lo stato di una build in corso. Per ottenere lo stato delle build in sospeso, si utilizza la seguente chiamata:

```
http://host:port/toastergui/api/building
```

Assicurarsi di specificare host e porta. L'output è un file JSON che elenca tutte le build in corso. Questo file include il tempo in secondi trascorso dall'avvio di ciascuna build, nonché l'avanzamento della clonazione, dell'analisi e dell'esecuzione dei task. Ecco un esempio di output per una build in corso:

```
{ "count": 1,
  "building": [
    { "machine": "beaglebone",
      "seconds": "463.869",
      "task": "927:2384",
      "distro": "poky",
      "clone": "1:1",
      "id": 2,
      "start": "2017-09-22T09:31:44.887Z",
      "name": "20170922093200",
      "parse": "818:818",
      "project": "my_rocko",
      "target": "core-image-minimal"
    }
  ]
}
```

I dati JSON per questa query vengono restituiti su una singola riga. Nell'esempio precedente, la riga è stata suddivisa artificialmente per una migliore leggibilità.

## Verifica dello Stato delle Build Completate

Una volta completata una build, è possibile visualizzarne lo stato utilizzando la seguente chiamata:

```
http://host:port/toastergui/api/builds
```

Assicurarsi di specificare host e porta. L'output è un file JSON che elenca tutte le build completate e include informazioni di riepilogo. Ecco un esempio di output per una build completata:

```
{
  "count": 1,
  "builds": [
    {
      "distro": "poky",
      "errors": 0,
      "machine": "beaglebone",
      "project": "my_rocko",
      "stop": "2017-09-22T09:26:36.017Z",
      "target": "quilt-native",
      "seconds": "78.193",
      "outcome": "Succeeded",
      "id": 1,
      "start": "2017-09-22T09:25:17.824Z",
      "warnings": 1,
      "name": "20170922092618"
    }
  ]
}
```

I dati JSON per questa query vengono restituiti su una singola riga. Nell'esempio precedente, la riga è stata suddivisa artificialmente per una migliore leggibilità.

### Determinazione dello Stato di una Build Specifica

A volte è utile determinare lo stato di una build specifica. Per ottenere lo stato di una build specifica, utilizzare la seguente chiamata:

```
http://host:port/toastergui/api/build/ID
```

Assicurarsi di specificare host, porta e ID. È possibile trovare il valore di ID dalla query Builds Completed. Assicurarsi di specificare host, porta e ID. È possibile trovare il valore di ID dalla query "[Verifica dello Stato delle Build Completate](#)" per ulteriori informazioni.

L'output è un file JSON che elenca la build specifica e include informazioni di riepilogo. Ecco un esempio di output per una build specifica:

```
{
  "build": {
    "distro": "poky",
    "errors": 0,
    "machine": "beaglebone",
    "project": "my_rocko",
    "stop": "2017-09-22T09:26:36.017Z",
    "target": "quilt-native",
    "seconds": "78.193",
    "outcome": "Succeeded",
    "id": 1,
    "start": "2017-09-22T09:25:17.824Z",
    "warnings": 1,

```

(continues on next page)

(continua dalla pagina precedente)

```

    "name": "20170922092618",
    "cooker_log": "/opt/user/poky/build-toaster-2/tmp/log/cooker/beaglebone/build_
↪20170922_022607.991.log"
  }
}

```

I dati JSON per questa query vengono restituiti su una singola riga. Nell'esempio precedente, la riga è stata suddivisa artificialmente per una migliore leggibilità.

### 13.4.5 Comandi Utili

Oltre all'interfaccia utente web e agli script che avviano e arrestano Toaster, sono disponibili comandi da riga di comando tramite lo script di gestione `manage.py`. È possibile trovare la documentazione generale su `manage.py` sul sito di [Django](#). Tuttavia, sono stati creati diversi comandi `manage.py` specifici per Toaster, utilizzati per controllare la configurazione e le attività di back-end. È possibile trovare questi comandi nella *Source Directory* (ad esempio poky) in `bitbake/lib/manage.py`. Questa sezione documenta tali comandi.

#### Nota

- Quando si utilizzano i comandi `manage.py` con una configurazione di default, è necessario assicurarsi che la directory di lavoro sia impostata sulla *Build Directory*. Utilizzando i comandi `manage.py` dalla *Build Directory*, Toaster può trovare il file `toaster.sqlite`, che si trova nella *Build Directory*.
- Per configurazioni di database non predefinite, è possibile utilizzare i comandi `manage.py` da una directory diversa da *Build Directory*. A tal fine, il file `toastermain/settings.py` deve essere configurato in modo da puntare al backend del database corretto.

#### **buildslist**

Il comando `buildslist` elenca tutte le build registrate da Toaster. Per accedervi, procedere come segue:

```
$ bitbake/lib/toaster/manage.py buildslist
```

Il comando restituisce un elenco, comprensivo di identificativi numerici, delle build registrate da Toaster nel database corrente.

Si deve eseguire il comando `buildslist` prima di identificare le build esistenti nel database prima di usare il comando *builddelete*. Ecco un esempio che presuppone i nomi di default per repository e della *Build Directory*:

```
$ cd poky/build
$ python ../bitbake/lib/toaster/manage.py buildslist
```

Se il database di Toaster contenesse una sola build, il comando *buildslist* restituirebbe un output simile al seguente:

```
1: qemux86 poky core-image-minimal
```

### **builddelete**

Il comando `builddelete` elimina i dati associati a una build. Per accedervi, procedere come segue:

```
$ bitbake/lib/toaster/manage.py builddelete build_id
```

Il comando elimina tutti i dati del `build_id` specificato. Questo comando è utile per rimuovere i dati vecchi e inutilizzati dal database.

Prima di eseguire il comando `builddelete`, è necessario ottenere l'ID associato alle build utilizzando il comando *buildslist*.

### **perf**

Il comando `perf` misura le prestazioni di Toaster. È possibile accedervi nel seguente modo:

```
$ bitbake/lib/toaster/manage.py perf
```

Questo comando esegue un controllo di base che restituisce i tempi di caricamento delle pagine per identificare eventuali problemi di prestazioni.

### **checksettings**

Il comando `checksettings` verifica le impostazioni di Toaster esistenti. È possibile accedervi nel seguente modo:

```
$ bitbake/lib/toaster/manage.py checksettings
```

Toaster utilizza impostazioni basate sul database per configurare i task di compilazione. Il comando `checksettings` verifica che le impostazioni del database siano valide, ovvero che contengano le informazioni minime necessarie per avviare una build.

Affinché il comando `checksettings` funzioni, il database deve essere configurato correttamente e non contenere dati preesistenti. Per verificare che il database sia pronto, è possibile eseguire i seguenti comandi:

```
$ bitbake/lib/toaster/manage.py syncdb
$ bitbake/lib/toaster/manage.py migrate orm
$ bitbake/lib/toaster/manage.py migrate bldcontrol
```

Dopo aver eseguito questi comandi, è possibile eseguire il comando `checksettings`.

### **runbuilds**

Il comando `runbuilds` avvia le build pianificate. Per accedervi, procedere come segue:

```
$ bitbake/lib/toaster/manage.py runbuilds
```

Il comando `runbuilds` verifica se nel database sono presenti build pianificate e, in caso affermativo, le avvia in base alla pianificazione. Il comando restituisce un valore al termine delle build, ma prima del loro completamento. L'interfaccia di registrazione di Toaster registra e aggiorna il database al termine delle build.

The Yocto Project ®

<[docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org)>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.

---

## Manuale dell'Ambiente di Test di Yocto Project

---

### 14.1 The Yocto Project Test Environment Manual

#### 14.1.1 Benvenuti!

Welcome to the Yocto Project Test Environment Manual, which contains information about the testing environment used by the Yocto Project to make sure each major and minor release works as intended. All the project's testing infrastructure and processes are publicly visible and available so that the community can see what testing is being performed, how it's being done and the current status of the tests and the project at any given time. It is intended that other organizations can leverage off the process and testing environment used by the Yocto Project to create their own automated, production test environment, building upon the foundations from the project core.

This manual is a work in progress and is being loaded initially with information from the README files and notes from key engineers:

- *yocto-autobuilder2*: This [README.md](#) is the main README which details how to set up the Yocto Project Autobuilder. The [yocto-autobuilder2 repository](#) represents the Yocto Project's console UI plugin to Buildbot and the configuration necessary to configure Buildbot to perform the testing the project requires.
- *yocto-autobuilder-helper*: This [README](#) and repository contains Yocto Project Autobuilder Helper scripts and configuration. The [yocto-autobuilder-helper repository](#) contains the "glue" logic that defines which tests to run and how to run them. As a result, it can be used by any Continuous Improvement (CI) system to run builds, support getting the correct code revisions, configure builds and layers, run builds, and collect results. The code is independent of any CI system, which means the code can work with [Buildbot](#), [Jenkins](#), or others. This repository has a branch per release of the project defining the tests to run on a per-release basis.

### 14.1.2 Yocto Project Autobuilder Overview

The Yocto Project Autobuilder collectively refers to the software, tools, scripts, and procedures used by the Yocto Project to test released software across supported hardware in an automated and regular fashion. Basically, during the development of a Yocto Project release, the Autobuilder tests if things work. The Autobuilder builds all test targets and runs all the tests.


The Yocto Project uses standard upstream Buildbot to drive its integration and testing. Buildbot has a plug-in interface that the Yocto Project customizes using code from the `yocto-autobuilder2` repository, adding its own console UI plugin. The resulting UI plug-in allows you to visualize builds in a way suited to the project's needs.

A `helper` layer provides configuration and job management through scripts found in the `yocto-to-autobuilder-helper` repository. The `helper` layer contains the bulk of the build configuration information and is release-specific, which makes it highly customizable on a per-project basis. The layer is CI system-agnostic and contains a number of Helper scripts that can generate build configurations from simple JSON files.

#### **i** Nota

The project uses Buildbot for historical reasons but also because many of the project developers have knowledge of Python. It is possible to use the outer layers from another Continuous Integration (CI) system such as [Jenkins](#) instead of Buildbot.

The following figure shows the Yocto Project Autobuilder stack with a topology that includes a controller and a cluster of workers:





### 14.1.3 Yocto Project Tests --- Types of Testing Overview

The Autobuilder tests different elements of the project by using the following types of tests:

- *Build Testing*: Tests whether specific configurations build by varying *MACHINE*, *DISTRO*, other configuration options, and the specific target images being built (or *world*). This is used to trigger builds of all the different test configurations on the Autobuilder. Builds usually cover many different targets for different architectures, machines, and distributions, as well as different configurations, such as different init systems. The Autobuilder tests literally hundreds of configurations and targets.
  - *Sanity Checks During the Build Process*: Tests initiated through the *insane* class. These checks ensure the output of the builds are correct. For example, does the ELF architecture in the generated binaries match the target system? ARM binaries would not work in a MIPS system!
- *Build Performance Testing*: Tests whether or not commonly used steps during builds work efficiently and avoid regressions. Tests to time commonly used usage scenarios are run through *oe-build-perf-test*. These tests are run on isolated machines so that the time measurements of the tests are accurate and no other processes interfere with the timing results. The project currently tests performance on two different distributions, Fedora and Ubuntu, to ensure we have no single point of failure and can ensure the different distros work effectively.
- *eSDK Testing*: Image tests initiated through the following command:

```
$ bitbake image -c testSDKext
```

The tests use the *testSDK* class and the *do\_testSDKext* task.

- *Feature Testing*: Various scenario-based tests are run through the *OpenEmbedded Self test (oe-selftest)*. We test *oe-selftest* on each of the main distributions we support.
- *Image Testing*: Image tests initiated through the following command:

```
$ bitbake image -c testImage
```

The tests use the *testImage* class and the *do\_testImage* task. See the *Performing Automated Runtime Testing* section of the Yocto Project Test Environment Manual for more information.

- *Layer Testing*: The Autobuilder has the possibility to test whether specific layers work with the test of the system. The layers tested may be selected by members of the project. Some key community layers are also tested periodically.
- *Package Testing*: A Package Test (*ptest*) runs tests against packages built by the OpenEmbedded build system on the target machine. See the *Testing Packages With ptest* section in the Yocto Project Test Environment Manual and the "*Ptest*" Wiki page for more information on *Ptest*.
- *SDK Testing*: Image tests initiated through the following command:

```
$ bitbake image -c testSDK
```

The tests use the *testSDK* class and the *do\_testSDK* task.

- *Unit Testing*: Unit tests on various components of the system run through *bitbake-selftest* and *oe-selftest*.

- *Automatic Upgrade Helper:* This target tests whether new versions of software are available and whether we can automatically upgrade to those new versions. If so, this target emails the maintainers with a patch to let them know this is possible.

### 14.1.4 How Tests Map to Areas of Code

Tests map into the codebase as follows:

- *bitbake-selftest:*

These tests are self-contained and test BitBake as well as its APIs, which include the fetchers. The tests are located in `bitbake/lib/*/tests`.

Some of these tests run the `bitbake` command, so `bitbake/bin` must be added to the `PATH` before running `bitbake-selftest`. From within the BitBake repository, run the following:

```
$ export PATH=$PWD/bin:$PATH
```

After that, you can run the selftest script:

```
$ bitbake-selftest
```

The default output is quiet and just prints a summary of what was run. To see more information, there is a verbose option:

```
$ bitbake-selftest -v
```

To skip tests that access the Internet, use the `BB_SKIP_NETTESTS` variable when running `bitbake-selftest` as follows:

```
$ BB_SKIP_NETTESTS=yes bitbake-selftest
```

Use this option when you wish to skip tests that access the network, which are mostly necessary to test the fetcher modules. To specify individual test modules to run, append the test module name to the `bitbake-selftest` command. For example, to specify the tests for `bb.tests.data.DataExpansions`, run:

```
$ bitbake-selftest bb.tests.data.DataExpansions
```

You can also specify individual tests by defining the full name and module plus the class path of the test, for example:

```
$ bitbake-selftest bb.tests.data.DataExpansions.test_one_var
```

The tests are based on [Python unittest](#).

- *oe-selftest:*
  - These tests use OE to test the workflows, which include testing specific features, behaviors of tasks, and API unit tests.

- The tests can take advantage of parallelism through the `-j` option, which can specify a number of threads to spread the tests across. Note that all tests from a given class of tests will run in the same thread. To parallelize large numbers of tests you can split the class into multiple units.
- The tests are based on [Python unittest](#).
- The code for the tests resides in `meta/lib/oeqa/selftest/cases/`.
- To run all the tests, enter the following command:

```
$ oe-selftest -a
```

- To run a specific test, use the following command form where `testname` is the name of the specific test:

```
$ oe-selftest -r <testname>
```

For example, the following command would run the `tinfoil getVar` API test:

```
$ oe-selftest -r tinfoil.TinfoilTests.test_getvar
```

It is also possible to run a set of tests. For example the following command will run all of the `tinfoil` tests:

```
$ oe-selftest -r tinfoil
```

- *testimage:*

- These tests build an image, boot it, and run tests against the image's content.
- The code for these tests resides in `meta/lib/oeqa/runtime/cases/`.
- You need to set the *IMAGE\_CLASSES* variable as follows:

```
IMAGE_CLASSES += "testimage"
```

- Run the tests using the following command form:

```
$ bitbake image -c testimage
```

- *testsdk:*

- These tests build an SDK, install it, and then run tests against that SDK.
- The code for these tests resides in `meta/lib/oeqa/sdk/cases/`.
- Run the test using the following command form:

```
$ bitbake image -c testsdk
```

- *testsdk\_ext:*

- These tests build an extended SDK (eSDK), install that eSDK, and run tests against the eSDK.
- The code for these tests resides in `meta/lib/oeqa/sdkext/cases/`.

- To run the tests, use the following command form:

```
$ bitbake image -c testSDKext
```

- *oe-build-perf-test*:

- These tests run through commonly used usage scenarios and measure the performance times.
- The code for these tests resides in `meta/lib/oeqa/buildperf`.
- To run the tests, use the following command form:

```
$ oe-build-perf-test <options>
```

The command takes a number of options, such as where to place the test results. The Autobuilder Helper Scripts include the `build-perf-test-wrapper` script with examples of how to use the `oe-build-perf-test` from the command line.

Use the `oe-git-archive` command to store test results into a Git repository.

Use the `oe-build-perf-report` command to generate text reports and HTML reports with graphs of the performance data. See [html](#) and [txt](#) examples.

- The tests are contained in `meta/lib/oeqa/buildperf/test_basic.py`.

## 14.1.5 Test Examples

This section provides example tests for each of the tests listed in the *How Tests Map to Areas of Code* section.

- `oe-selftest` testcases reside in the `meta/lib/oeqa/selftest/cases` directory.
- `bitbake-selftest` testcases reside in the `bitbake/lib/bb/tests/` directory.

### `bitbake-selftest`

A simple test example from `bitbake/lib/bb/tests/data.py` is:

```
class DataExpansions(unittest.TestCase):
    def setUp(self):
        self.d = bb.data.init()
        self.d["foo"] = "value_of_foo"
        self.d["bar"] = "value_of_bar"
        self.d["value_of_foo"] = "value_of_'value_of_foo'"

    def test_one_var(self):
        val = self.d.expand("${foo}")
        self.assertEqual(str(val), "value_of_foo")
```

In this example, a `DataExpansions` class of tests is created, derived from standard Python `unittest`. The class has a common `setUp` function which is shared by all the tests in the class. A simple test is then added to test that when a variable is expanded, the correct value is found.

BitBake selftests are straightforward [Python unittest](#). Refer to the [Python unittest documentation](#) for additional information on writing such tests.

### oe-selftest

These tests are more complex due to the setup required behind the scenes for full builds. Rather than directly using [Python unittest](#), the code wraps most of the standard objects. The tests can be simple, such as testing a command from within the OE build environment using the following example:

```
class BitbakeLayers (OESelftestTestCase):
    def test_bitbakelayers_showcrossdepends (self):
        result = runCmd('bitbake-layers show-cross-depends')
        self.assertTrue('aspell' in result.output, msg = "No dependencies were_
↳ shown. bitbake-layers show-cross-depends output: %s"% result.output)
```

This example, taken from `meta/lib/oeqa/selftest/cases/bblayers.py`, creates a testcase from the `OESelftestTestCase` class, derived from `unittest.TestCase`, which runs the `bitbake-layers` command and checks the output to ensure it contains something we know should be here.

The `oeqa.utils.commands` module contains Helpers which can assist with common tasks, including:

- *Obtaining the value of a bitbake variable:* Use `oeqa.utils.commands.get_bb_var()` or use `oeqa.utils.commands.get_bb_vars()` for more than one variable
- *Running a bitbake invocation for a build:* Use `oeqa.utils.commands.bitbake()`
- *Running a command:* Use `oeqa.utils.commands.runCmd()`

There is also a `oeqa.utils.commands.rungemu()` function for launching the `rungemu` command for testing things within a running, virtualized image.

You can run these tests in parallel. Parallelism works per test class, so tests within a given test class should always run in the same build, while tests in different classes or modules may be split into different builds. There is no data store available for these tests since the tests launch the `bitbake` command and exist outside of its context. As a result, common BitBake library functions (`bb.*`) are also unavailable.

### testimage

These tests are run once an image is up and running, either on target hardware or under QEMU. As a result, they are assumed to be running in a target image environment, as opposed to in a host build environment. A simple example from `meta/lib/oeqa/runtime/cases/python.py` contains the following:

```
class PythonTest (OERuntimeTestCase):
    @OETestDepends(['ssh.SSHTest.test_ssh'])
    @OEHasPackage(['python3-core'])
    def test_python3 (self):
        cmd = "python3 -c \"import codecs; print(codecs.encode('Uryyb, jbeyq',
↳ 'rot13'))\""
        status, output = self.target.run(cmd)
```

(continues on next page)

(continua dalla pagina precedente)

```
msg = 'Exit status was not 0. Output: %s' % output
self.assertEqual(status, 0, msg=msg)
```

In this example, the `OERuntimeTestCase` class wraps `unittest.TestCase`. Within the test, `self.target` represents the target system, where commands can be run using the `run()` method.

To ensure certain tests or package dependencies are met, you can use the `OETestDepends` and `OEHasPackage` decorators. For example, the test in this example would only make sense if `python3-core` is installed in the image.

### testsdk\_ext

These tests are run against built extensible SDKs (eSDKs). The tests can assume that the eSDK environment has already been set up. An example from `meta/lib/oeqa/sdk/cases/devtool.py` contains the following:

```
class DevtoolTest(OESDKExtTestCase):
    @classmethod
    def setUpClass(cls):
        myapp_src = os.path.join(cls.tc.esdk_files_dir, "myapp")
        cls.myapp_dst = os.path.join(cls.tc.sdk_dir, "myapp")
        shutil.copytree(myapp_src, cls.myapp_dst)
        subprocess.check_output(['git', 'init', '.'], cwd=cls.myapp_dst)
        subprocess.check_output(['git', 'add', '.'], cwd=cls.myapp_dst)
        subprocess.check_output(['git', 'commit', '-m', "test commit"], cwd=cls.
↪myapp_dst)

    @classmethod
    def tearDownClass(cls):
        shutil.rmtree(cls.myapp_dst)
    def _test_devtool_build(self, directory):
        self._run('devtool add myapp %s' % directory)
        try:
            self._run('devtool build myapp')
        finally:
            self._run('devtool reset myapp')
    def test_devtool_build_make(self):
        self._test_devtool_build(self.myapp_dst)
```

In this example, the `devtool` command is tested to see whether a sample application can be built with the `devtool build` command within the eSDK.

### testsdk

These tests are run against built SDKs. The tests can assume that an SDK has already been extracted and its environment file has been sourced. A simple example from `meta/lib/oeqa/sdk/cases/python.py` contains the following:

```

class Python3Test(OESDKTestCase):
    def setUp(self):
        if not (self.tc.hasHostPackage("nativesdk-python3-core") or
                self.tc.hasHostPackage("python3-core-native")):
            raise unittest.SkipTest("No python3 package in the SDK")

    def test_python3(self):
        cmd = "python3 -c \\\"import codecs; print(codecs.encode('Uryyb, jbeyq',
↪ 'rot13'))\\\""
        output = self._run(cmd)
        self.assertEqual(output, "Hello, world\\n")

```

In this example, if `nativesdk-python3-core` has been installed into the SDK, the code runs the `python3` interpreter with a basic command to check it is working correctly. The test would only run if Python3 is installed in the SDK.

#### oe-build-perf-test

The performance tests usually measure how long operations take and the resource utilization as that happens. An example from `meta/lib/oeqa/buildperf/test_basic.py` contains the following:

```

class Test3(BuildPerfTestCase):
    def test3(self):
        """Bitbake parsing (bitbake -p)"""
        # Drop all caches and parse
        self.rm_cache()
        oe.path.remove(os.path.join(self.bb_vars['TMPDIR'], 'cache'), True)
        self.measure_cmd_resources(['bitbake', '-p'], 'parse_1',
                                   'bitbake -p (no caches)')
        # Drop tmp/cache
        oe.path.remove(os.path.join(self.bb_vars['TMPDIR'], 'cache'), True)
        self.measure_cmd_resources(['bitbake', '-p'], 'parse_2',
                                   'bitbake -p (no tmp/cache)')
        # Parse with fully cached data
        self.measure_cmd_resources(['bitbake', '-p'], 'parse_3',
                                   'bitbake -p (cached)')

```

This example shows how three specific parsing timings are measured, with and without various caches, to show how BitBake's parsing performance trends over time.

### 14.1.6 Considerations When Writing Tests

When writing good tests, there are several things to keep in mind. Since things running on the Autobuilder are accessed concurrently by multiple workers, consider the following:

**Running "cleanall" is not permitted.**

This can delete files from `DL_DIR` which would potentially break other builds running in parallel. If this is required, `DL_DIR` must be set to an isolated directory.

**Running "cleansstate" is not permitted.**

This can delete files from `SSTATE_DIR` which would potentially break other builds running in parallel. If this is required, `SSTATE_DIR` must be set to an isolated directory. Alternatively, you can use the `-f` option with the `bitbake` command to "taint" tasks by changing the sstate checksums to ensure sstate cache items will not be reused.

**Tests should not change the metadata.**

This is particularly true for oe-selftests since these can run in parallel and changing metadata leads to changing checksums, which confuses BitBake while running in parallel. If this is necessary, copy layers to a temporary location and modify them. Some tests need to change metadata, such as the devtool tests. To protect the metadata from changes, set up temporary copies of that data first.

## 14.2 Project Testing and Release Process

### 14.2.1 Day to Day Development

This section details how the project tests changes, through automation on the Autobuilder or with the assistance of QA teams, through to making releases.

The project aims to test changes against our test matrix before those changes are merged into the master branch. As such, changes are queued up in batches either in the `master-next` branch in the main trees, or in user trees such as `ross/mut` in `poky-contrib` (Ross Burton helps review and test patches and this is his testing tree).

We have two broad categories of test builds, including "full" and "quick". On the Autobuilder, these can be seen as "a-quick" and "a-full", simply for ease of sorting in the UI. Use our Autobuilder [console view](#) to see where we manage most test-related items.

Builds are triggered manually when the test branches are ready. The builds are monitored by the SWAT team. For additional information, see [https://wiki.yoctoproject.org/wiki/Yocto\\_Build\\_Failure\\_Swat\\_Team](https://wiki.yoctoproject.org/wiki/Yocto_Build_Failure_Swat_Team). If successful, the changes would usually be merged to the `master` branch. If not successful, someone would respond to the changes on the mailing list explaining that there was a failure in testing. The choice of quick or full would depend on the type of changes and the speed with which the result was required.

The Autobuilder does build the `master` branch once daily for several reasons, in particular, to ensure the current `master` branch does build, but also to keep (`yocto-testresults`), (`buildhistory`), and our `sstate` up to date. On the weekend, there is a `master-next` build instead to ensure the test results are updated for the less frequently run targets.

Performance builds (`buildperf-*` targets in the console) are triggered separately every six hours and automatically push their results to the `buildstats` repository.

The "quick" targets have been selected to be the ones which catch the most failures or give the most valuable data. We run "fast" ptests in this case for example but not the ones which take a long time. The quick target doesn't include `*-lsb` builds for all architectures, some `world` builds and doesn't trigger performance tests or `ltp` testing. The full build includes all these things and is slower but more comprehensive.



## 14.2.2 Release Builds

The project typically has two major releases a year with a six month cadence in April and October. Between these there would be a number of milestone releases (usually four) with the final one being stabilization only along with point releases of our stable branches.

The build and release process for these project releases is similar to that in *Day to Day Development*, in that the a-full target of the Autobuilder is used but in addition the form is configured to generate and publish artifacts and the milestone number, version, release candidate number and other information is entered. The box to "generate an email to QA" is also checked.

When the build completes, an email is sent out using the `send-qa-email` script in the `yocto-autobuilder-helper` repository to the list of people configured for that release. Release builds are placed into a directory in <https://valkyrie.yocto.io/pub/releases> on the Autobuilder which is included in the email. The process from here is more manual and control is effectively passed to release engineering. The next steps include:

- QA teams respond to the email saying which tests they plan to run and when the results will be available.
- QA teams run their tests and share their results in the `yocto-testresults-contrib` repository, along with a summary of their findings.
- Release engineering prepare the release as per their process.
- Test results from the QA teams are included into the release in separate directories and also uploaded to the `yocto-testresults` repository alongside the other test results for the given revision.
- The QA report in the final release is regenerated using `resulttool` to include the new test results and the test summaries from the teams (as headers to the generated report).
- The release is checked against the release checklist and release readiness criteria.
- A final decision on whether to release is made by the YP TSC who have final oversight on release readiness.

## 14.3 Testing Packages With ptest

A Package Test (ptest) runs tests against packages built by the OpenEmbedded build system on the target machine. A ptest contains at least two items: the actual test, and a shell script (`run-ptest`) that starts the test. The shell script that starts the test must not contain the actual test --- the script only starts the test. On the other hand, the test can be anything from a simple shell script that runs a binary and checks the output to an elaborate system of test binaries and data files.

The test generates output in the format used by Automake:

```
result: testname
```

where the result can be `PASS`, `FAIL`, or `SKIP`, and the testname can be any identifying string.

For a list of Yocto Project recipes that are already enabled with ptest, see the [Ptest](#) wiki page.

**i Nota**

A recipe is "ptest-enabled" if it inherits the *ptest* class.

### 14.3.1 Adding ptest to Your Build

Adding package testing to your image is done in two steps:

1. Select that all ptest packages should be built and packaged, and
2. Identify which of those ptest packages to add to your image.

First, in order to build all ptest packages, add the following line to a *configuration file*:

```
DISTRO_FEATURES:append = " ptest"
```

Note that this will cause all ptest packages to be built and packaged, but will not add any of those packages to your image; that comes in the next step. You can then add ptest packages to your image in one of two ways.

1. If you want to add *all* of the generated ptest packages, add the line:

```
EXTRA_IMAGE_FEATURES += "ptest-pkgs"
```

2. On the other hand, if you want to add only a select few of the ptest packages, you can use some variation of:

```
IMAGE_INSTALL:append = " e2fsprogs-ptest zlib-ptest"
```

Once your build is complete, the ptest files are installed into the `/usr/lib/package/ptest` directory within the image, where *package* is the name of the package.

**i Nota**

If you want to list all ptest packages currently available from the local package feed that *could* be installed in your image (not just the ones you're selecting), you can use the `oe-pkgdata-util` command:

```
$ oe-pkgdata-util list-pkgs "*-ptest"
acl-ptest
attr-ptest
bash-ptest
... etc etc ...
```

### 14.3.2 Running ptest

The `ptest-runner` package installs a shell script that loops through all installed ptest test suites and runs them in sequence.

During the execution `ptest-runner` keeps count of total and failed ptests. At end the execution summary is written to the console. If any of the `run-ptest` fails, `ptest-runner` returns '1'.

The inclusion of any ptest packages in your image will automatically include `ptest-runner` in your image.

### 14.3.3 Getting Your Package Ready

In order to enable a recipe to run installed `ptest`s on target hardware, you need to prepare the recipes that build the packages you want to test. Here is what you have to do for each recipe:

- *Be sure the recipe inherits the `ptest` class:* Include the following line in each recipe:

```
inherit ptest
```

#### Nota

Classes for common frameworks already exist in *OpenEmbedded-Core (OE-Core)*, such as:

- `go-ptest`
- `ptest-cargo`
- `ptest-gnome`
- `ptest-perl`
- `ptest-python-pytest`

Inheriting these classes with the `inherit` keyword in your recipe will make the next steps automatic.

- *Create `run-ptest`:* This script starts your test. Locate the script where you will refer to it using `SRC_URI`. Be sure `run-ptest` exits with 0 to mark it as successfully executed otherwise will be marked as fail. Here is an example that starts a test for `dbus`:

```
#!/bin/sh
cd test
make -k runtest-TESTS
```

- *Return an appropriate exit code:* The `run-ptest` script must return 0 on success, 1 on failure. This is needed by `ptest-runner` to keep track of the successful and failed tests.
- *Make sure the test prints at least one test result:* The execution of the `run-ptest` script must result in at least one test result output on the console, with the following format:

```
result: testname
```

Where `result` can be one of `PASS`, `SKIP`, or `FAIL`. `testname` can be any name.

There can be as many test results as desired.

This information is read by the `testimage` class and `logparser` module.

- *Ensure dependencies are met:* If the test adds build or runtime dependencies that normally do not exist for the package (such as requiring "make" to run the test suite), use the `DEPENDS` and `RDEPENDS` variables in your recipe in order for the package to meet the dependencies. Here is an example where the package has a runtime dependency on "make":

```
RDEPENDS:${PN}-ptest += "make"
```

- *Add a function to build the test suite:* Not many packages support cross-compilation of their test suites. Consequently, you usually need to add a cross-compilation function to the package.

Many packages based on Automake compile and run the test suite by using a single command such as `make check`. However, the host `make check` builds and runs on the same computer, while cross-compiling requires that the package is built on the host but executed for the target architecture (though often, as in the case for `ptest`, the execution occurs on the host). The built version of Automake that ships with the Yocto Project includes a patch that separates building and execution. Consequently, packages that use the unaltered, patched version of `make check` automatically cross-compile.

Regardless, you still must add a `do_compile_ptest` function to build the test suite. Add a function similar to the following to your recipe:

```
do_compile_ptest() {  
    oe_runmake buildtest-TESTS  
}
```

- *Ensure special configurations are set:* If the package requires special configurations prior to compiling the test code, you must insert a `do_configure_ptest` function into the recipe.
- *Install the test suite:* The `ptest` class automatically copies the file `run-ptest` to the target and then runs `make install-ptest` to run the tests. If this is not enough, you need to create a `do_install_ptest` function and make sure it gets called after the "make install-ptest" completes.

## 14.4 Performing Automated Runtime Testing

The OpenEmbedded build system makes available a series of automated tests for images to verify runtime functionality. You can run these tests on either QEMU or actual target hardware. Tests are written in Python making use of the `unittest` module, and the majority of them run commands on the target system over SSH. This section describes how you set up the environment to use these tests, run available tests, and write and add your own tests.

For information on the test and QA infrastructure available within the Yocto Project, see the "[Test e Garanzia di Qualità](#)" section in the Yocto Project Reference Manual.

### 14.4.1 Enabling Tests

Depending on whether you are planning to run tests using QEMU or on the hardware, you have to take different steps to enable the tests. See the following subsections for information on how to enable both types of tests.

#### Enabling Runtime Tests on QEMU

In order to run tests, you need to do the following:

- *Set up to avoid interaction with `sudo` for networking:* To accomplish this, you must do one of the following:
  - Add `NOPASSWD` for your user in `/etc/sudoers` either for all commands or just for `runqemu-ifup`. You must provide the full path as that can change if you are using multiple clones of the source repository.

**Nota**

On some distributions, you also need to comment out "Defaults requiretty" in `/etc/sudoers`.

- Manually configure a tap interface for your system.
- Run as root the script in `scripts/runqemu-gen-tapdevs`, which should generate a list of tap devices. This is the option typically chosen for Autobuilder-type environments.

**Nota**

- \* Be sure to use an absolute path when calling this script with `sudo`.
- \* Ensure that your host has the package `iptables` installed.
- \* The package recipe `qemu-helper-native` is required to run this script. Build the package using the following command:

```
$ bitbake qemu-helper-native
```

- *Set the `DISPLAY` variable:* You need to set this variable so that you have an X server available (e.g. start `vncserver` for a headless machine).
- *Be sure your host's firewall accepts incoming connections from `192.168.7.0/24`:* Some of the tests (in particular DNF tests) start an HTTP server on a random high number port, which is used to serve files to the target. The DNF module serves `${WORKDIR}/oe-rootfs-repo` so it can run DNF channel commands. That means your host's firewall must accept incoming connections from `192.168.7.0/24`, which is the default IP range used for tap devices by `runqemu`.
- *Be sure your host has the correct packages installed:* Depending your host's distribution, you need to have the following packages installed:
  - Ubuntu and Debian: `sysstat` and `iproute2`
  - openSUSE: `sysstat` and `iproute2`
  - Fedora: `sysstat` and `iproute`
  - CentOS: `sysstat` and `iproute`

Once you start running the tests, the following happens:

1. A copy of the root filesystem is written to `${WORKDIR}/testimage`.
2. The image is booted under QEMU using the standard `runqemu` script.
3. A default timeout of 500 seconds occurs to allow for the boot process to reach the login prompt. You can change the timeout period by setting `TEST_QEMUBOOT_TIMEOUT` in a *configuration file*.
4. Once the boot process is reached and the login prompt appears, the tests run. The full boot log is written to `${WORKDIR}/testimage/qemu_boot_log`.
5. Each test module loads in the order found in `TEST_SUITES`. You can find the full output of the commands run over SSH in `${WORKDIR}/testimage/ssh_target_log`.

6. If no failures occur, the task running the tests ends successfully. You can find the output from the `unittest` in the task log at `${WORKDIR}/temp/log.do_testimage`.

## Enabling Runtime Tests on Hardware

The OpenEmbedded build system can run tests on real hardware, and for certain devices it can also deploy the image to be tested onto the device beforehand.

For automated deployment, a "controller image" is installed onto the hardware once as part of setup. Then, each time tests are to be run, the following occurs:

1. The controller image is booted into and used to write the image to be tested to a second partition.
2. The device is then rebooted using an external script that you need to provide.
3. The device boots into the image to be tested.

When running tests (independent of whether the image has been deployed automatically or not), the device is expected to be connected to a network on a pre-determined IP address. You can either use static IP addresses written into the image, or set the image to use DHCP and have your DHCP server on the test network assign a known IP address based on the MAC address of the device.

In order to run tests on hardware, you need to set `TEST_TARGET` to an appropriate value. For QEMU, you do not have to change anything, the default value is "qemu". For running tests on hardware, the following options are available:

- *"simpleremote"*: Choose "simpleremote" if you are going to run tests on a target system that is already running the image to be tested and is available on the network. You can use "simpleremote" in conjunction with either real hardware or an image running within a separately started QEMU or any other virtual machine manager.
- *"SystemdbootTarget"*: Choose "SystemdbootTarget" if your hardware is an EFI-based machine with `systemd-boot` as bootloader and `core-image-testmaster` (or something similar) is installed. Also, your hardware under test must be in a DHCP-enabled network that gives it the same IP address for each reboot.

If you choose "SystemdbootTarget", there are additional requirements and considerations. See the *"Selecting SystemdbootTarget"* section, which follows, for more information.

- *"BeagleBoneTarget"*: Choose "BeagleBoneTarget" if you are deploying images and running tests on the BeagleBone "Black" or original "White" hardware. For information on how to use these tests, see the comments at the top of the `BeagleBoneTarget meta-yocto-bsp/lib/oeqa/controllers/beaglebonetarget.py` file.
- *"GrubTarget"*: Choose "GrubTarget" if you are deploying images and running tests on any generic PC that boots using GRUB. For information on how to use these tests, see the comments at the top of the `GrubTarget meta-yocto-bsp/lib/oeqa/controllers/grubtarget.py` file.
- *"your-target"*: Create your own custom target if you want to run tests when you are deploying images and running tests on a custom machine within your BSP layer. To do this, you need to add a Python unit that defines the target class under `lib/oeqa/controllers/` within your layer. You must also provide an empty `__init__.py`. For examples, see files in `meta-yocto-bsp/lib/oeqa/controllers/`.

## Selecting SystemdbootTarget

If you did not set `TEST_TARGET` to "SystemdbootTarget", then you do not need any information in this section. You can skip down to the "Running Tests" section.

If you did set `TEST_TARGET` to "SystemdbootTarget", you also need to perform a one-time setup of your controller image by doing the following:

1. *Set `EFI_PROVIDER`:* Be sure that `EFI_PROVIDER` is as follows:

```
EFI_PROVIDER = "systemd-boot"
```

2. *Build the controller image:* Build the `core-image-testmaster` image. The `core-image-testmaster` recipe is provided as an example for a "controller" image and you can customize the image recipe as you would any other recipe.

Image recipe requirements are:

- Inherits `core-image` so that kernel modules are installed.
- Installs normal linux utilities not BusyBox ones (e.g. `bash`, `coreutils`, `tar`, `gzip`, and `kmod`).
- Uses a custom `Initramfs` image with a custom installer. A normal image that you can install usually creates a single root filesystem partition. This image uses another installer that creates a specific partition layout. Not all Board Support Packages (BSPs) can use an installer. For such cases, you need to manually create the following partition layout on the target:
  - First partition mounted under `/boot`, labeled "boot".
  - The main root filesystem partition where this image gets installed, which is mounted under `/`.
  - Another partition labeled "testrootfs" where test images get deployed.

3. *Install image:* Install the image that you just built on the target system.

The final thing you need to do when setting `TEST_TARGET` to "SystemdbootTarget" is to set up the test image:

1. *Set up your `local.conf` file:* Make sure you have the following statements in your `build/conf/local.conf` file:

```
IMAGE_FSTYPES += "tar.gz"
IMAGE_CLASSES += "testimage"
TEST_TARGET = "SystemdbootTarget"
TEST_TARGET_IP = "192.168.2.3"
```

2. *Build your test image:* Use BitBake to build the image:

```
$ bitbake core-image-sato
```

## Power Control

For most hardware targets other than "simpleremote", you can control power:

- You can use `TEST_POWERCONTROL_CMD` together with `TEST_POWERCONTROL_EXTRA_ARGS` as a command that runs on the host and does power cycling. The test code passes one argument to that command: off, on or cycle (off then on). Here is an example that could appear in your `build/conf/local.conf` file:

```
TEST_POWERCONTROL_CMD = "powercontrol.exp test 10.11.12.1 nuc1"
```

In this example, the expect script does the following:

```
ssh test@10.11.12.1 "pyctl nuc1 arg"
```

It then runs a Python script that controls power for a label called `nuc1`.

#### Nota

You need to customize `TEST_POWERCONTROL_CMD` and `TEST_POWERCONTROL_EXTRA_ARGS` for your own setup. The one requirement is that it accepts "on", "off", and "cycle" as the last argument.

- When no command is defined, it connects to the device over SSH and uses the classic reboot command to reboot the device. Classic reboot is fine as long as the machine actually reboots (i.e. the SSH test has not failed). It is useful for scenarios where you have a simple setup, typically with a single board, and where some manual interaction is okay from time to time.

If you have no hardware to automatically perform power control but still wish to experiment with automated hardware testing, you can use the `dialog-power-control` script that shows a dialog prompting you to perform the required power action. This script requires either KDialog or Zenity to be installed. To use this script, set the `TEST_POWERCONTROL_CMD` variable as follows:

```
TEST_POWERCONTROL_CMD = "${COREBASE}/scripts/contrib/dialog-power-control"
```

## Serial Console Connection

For test target classes requiring a serial console to interact with the bootloader (e.g. BeagleBoneTarget and Grub-Target), you need to specify a command to use to connect to the serial console of the target machine by using the `TEST_SERIALCONTROL_CMD` variable and optionally the `TEST_SERIALCONTROL_EXTRA_ARGS` variable.

These cases could be a serial terminal program if the machine is connected to a local serial port, or a `telnet` or `ssh` command connecting to a remote console server. Regardless of the case, the command simply needs to connect to the serial console and forward that connection to standard input and output as any normal terminal program does. For example, to use the `picocom` terminal program on serial device `/dev/ttyUSB0` at 115200bps, you would set the variable as follows:

```
TEST_SERIALCONTROL_CMD = "picocom /dev/ttyUSB0 -b 115200"
```

For local devices where the serial port device disappears when the device reboots, an additional "serdevtry" wrapper script is provided. To use this wrapper, simply prefix the terminal command with `${COREBASE}/scripts/contrib/serdevtry`:

```
TEST_SERIALCONTROL_CMD = "${COREBASE}/scripts/contrib/serdevtry picocom -b 115200 /  
↪dev/ttyUSB0"
```



## 14.4.2 Running Tests

You can start the tests automatically or manually:

- *Automatically running tests:* To run the tests automatically after the OpenEmbedded build system successfully creates an image, first set the `TESTIMAGE_AUTO` variable to "1" in your `build/conf/local.conf` file in the *Build Directory*:

```
TESTIMAGE_AUTO = "1"
```

Next, build your image. If the image successfully builds, the tests run:

```
bitbake core-image-sato
```

- *Manually running tests:* To manually run the tests, first globally inherit the `testimage` class by editing your `build/conf/local.conf` file:

```
IMAGE_CLASSES += "testimage"
```

Next, use BitBake to run the tests:

```
bitbake -c testimage image
```

All test files reside in `meta/lib/oeqa/runtime/cases` in *OpenEmbedded-Core (OE-Core)*. A test name maps directly to a Python module. Each test module may contain a number of individual tests. Tests are usually grouped together by the area tested (e.g. tests for `systemd` reside in `meta/lib/oeqa/runtime/cases/systemd.py`).

You can add tests to any layer provided you place them in the proper area and you extend `BBPATH` in the `build/conf/local.conf` file as normal. Be sure that tests reside in `layer/lib/oeqa/runtime/cases`.

### Nota

Be sure that module names do not collide with module names used in the default set of test modules in `meta/lib/oeqa/runtime/cases`.

You can change the set of tests run by appending or overriding `TEST_SUITES` variable in `build/conf/local.conf`. Each name in `TEST_SUITES` represents a required test for the image. Test modules named within `TEST_SUITES` cannot be skipped even if a test is not suitable for an image (e.g. running the RPM tests on an image without `rpm`). Appending "auto" to `TEST_SUITES` causes the build system to try to run all tests that are suitable for the image (i.e. each test module may elect to skip itself).

The order you list tests in `TEST_SUITES` is important and influences test dependencies. Consequently, tests that depend on other tests should be added after the test on which they depend. For example, since the `ssh` test depends on the `ping` test, "ssh" needs to come after "ping" in the list. The test class provides no re-ordering or dependency handling.

**i Nota**

Each module can have multiple classes with multiple test methods. And, Python `unittest` rules apply.

Here are some things to keep in mind when running tests:

- The default tests for the image are defined as:

```
DEFAULT_TEST_SUITES:pn-image = "ping ssh df connman syslog xorg scp vnc date_
↳rpm dnf dmesg"
```

- Add your own test to the list of the by using the following:

```
TEST_SUITES:append = " mytest"
```

- Run a specific list of tests as follows:

```
TEST_SUITES = "test1 test2 test3"
```

Remember, order is important. Be sure to place a test that is dependent on another test later in the order.

### 14.4.3 Exporting Tests

You can export tests so that they can run independently of the build system. Exporting tests is required if you want to be able to hand the test execution off to a scheduler. You can only export tests that are defined in *TEST\_SUITES*.

If your image is already built, make sure the following are set in your *build/conf/local.conf* file:

```
IMAGE_CLASSES += "testexport"
TEST_TARGET_IP = "IP-address-for-the-test-target"
TEST_SERVER_IP = "IP-address-for-the-test-server"
```

You can then export the tests with the following BitBake command form:

```
$ bitbake image -c testexport
```

Exporting the tests places them in the *Build Directory* in *tmp/testimage/image*, which is controlled by the *TEST\_EXPORT\_DIR* variable.

You can now run the tests outside of the build environment:

```
$ cd tmp/testimage/image
$ ./oe-test runtime
```

**i Nota**

You might need to run the image under QEMU or deploy it to your hardware before you can run the tests.

Here is a complete example that shows IP addresses and uses the `core-image-sato` image:

```
IMAGE_CLASSES += "testexport"
TEST_TARGET_IP = "192.168.7.2"
TEST_SERVER_IP = "192.168.7.1"
```

Use BitBake to export the tests:

```
$ bitbake core-image-sato -c testexport
```

Run the tests outside of the build environment using the following:

```
$ cd tmp/testimage/core-image-sato
$ ./oe-test runtime
```

#### 14.4.4 Writing New Tests

As mentioned previously, all new test files need to be in the proper place for the build system to find them. New tests for additional functionality outside of the core should be added to the layer that adds the functionality, in `layer/lib/oeqa/runtime/cases` (as long as `BBPATH` is extended in the layer's `layer.conf` file as normal). Just remember the following:

- Filenames need to map directly to test (module) names.
- Do not use module names that collide with existing core tests.
- Minimally, an empty `__init__.py` file must be present in the runtime directory.

To create a new test, start by copying an existing module (e.g. `oe_syslog.py` or `gcc.py` are good ones to use). Test modules can use code from `meta/lib/oeqa/utils`, which are helper classes.

**i Nota**

Structure shell commands such that you rely on them and they return a single code for success. Be aware that sometimes you will need to parse the output. See the `df.py` and `date.py` modules for examples.

You will notice that all test classes inherit `oeRuntimeTest`, which is found in `meta/lib/oetest.py`. This base class offers some helper attributes, which are described in the following sections:

## Class Methods

Class methods are as follows:

- *hasPackage(pkg)*: Returns "True" if `pkg` is in the installed package list of the image, which is based on the manifest file that is generated during the *do\_rootfs* task.
- *hasFeature(feature)*: Returns "True" if the feature is in *IMAGE\_FEATURES* or *DISTRO\_FEATURES*.

## Class Attributes

Class attributes are as follows:

- *pscmd*: Equals "ps -ef" if `procps` is installed in the image. Otherwise, `pscmd` equals "ps" (busybox).
- *tc*: The called test context, which gives access to the following attributes:
  - *d*: The BitBake datastore, which allows you to use stuff such as `oeRuntimeTest.tc.d.getVar("VIRTUAL-RUNTIME_init_manager")`.
  - *testslst* and *testsrequired*: Used internally. The tests do not need these.
  - *filesdir*: The absolute path to `meta/lib/oeqa/runtime/files`, which contains helper files for tests meant for copying on the target such as small files written in C for compilation.
  - *target*: The target controller object used to deploy and start an image on a particular target (e.g. Qemu, SimpleRemote, and SystemdbootTarget). Tests usually use the following:
    - \* *ip*: The target's IP address.
    - \* *server\_ip*: The host's IP address, which is usually used by the DNF test suite.
    - \* *run(cmd, timeout=None)*: The single, most used method. This command is a wrapper for: `ssh root@host "cmd"`. The command returns a tuple: (status, output), which are what their names imply - the return code of "cmd" and whatever output it produces. The optional timeout argument represents the number of seconds the test should wait for "cmd" to return. If the argument is "None", the test uses the default instance's timeout period, which is 300 seconds. If the argument is "0", the test runs until the command returns.
    - \* *copy\_to(localpath, remotepath)*: `scp localpath root@ip:remotepath`.
    - \* *copy\_from(remotepath, localpath)*: `scp root@host:remotepath localpath`.

## Instance Attributes

There is a single instance attribute, which is `target`. The `target` instance attribute is identical to the class attribute of the same name, which is described in the previous section. This attribute exists as both an instance and class attribute so tests can use `self.target.run(cmd)` in instance methods instead of `oeRuntimeTest.tc.target.run(cmd)`.

### 14.4.5 Installing Packages in the DUT Without the Package Manager

When a test requires a package built by BitBake, it is possible to install that package. Installing the package does not require a package manager be installed in the device under test (DUT). It does, however, require an SSH connection and the target must be using the `sshcontrol` class.

#### Nota

This method uses `scp` to copy files from the host to the target, which causes permissions and special attributes to be lost.

A JSON file is used to define the packages needed by a test. This file must be in the same path as the file used to define the tests. Furthermore, the filename must map directly to the test module name with a `.json` extension.

The JSON file must include an object with the test name as keys of an object or an array. This object (or array of objects) uses the following data:

- "pkg" --- a mandatory string that is the name of the package to be installed.
- "rm" --- an optional boolean, which defaults to "false", that specifies to remove the package after the test.
- "extract" --- an optional boolean, which defaults to "false", that specifies if the package must be extracted from the package format. When set to "true", the package is not automatically installed into the DUT.

Here is an example JSON file that handles test "foo" installing package "bar" and test "foobar" installing packages "foo" and "bar". Once the test is complete, the packages are removed from the DUT:

```
{
  "foo": {
    "pkg": "bar"
  },
  "foobar": [
    {
      "pkg": "foo",
      "rm": true
    },
    {
      "pkg": "bar",
      "rm": true
    }
  ]
}
```

## 14.5 Understanding the Yocto Project Autobuilder

### 14.5.1 Execution Flow within the Autobuilder

The "a-full" and "a-quick" targets are the usual entry points into the Autobuilder and it makes sense to follow the process through the system starting there. This is best visualized from the [Autobuilder Console](#) view.

Each item along the top of that view represents some "target build" and these targets are all run in parallel. The 'full' build will trigger the majority of them, the "quick" build will trigger some subset of them. The Autobuilder effectively runs whichever configuration is defined for each of those targets on a separate buildbot worker. To understand the configuration, you need to look at the entry on `config.json` file within the [yocto-autobuilder-helper](#) repository. The targets are defined in the `overrides` section, a quick example could be `qemux86-64` which looks like:

```
"qemux86-64" : {
    "MACHINE" : "qemux86-64",
    "TEMPLATE" : "arch-qemu",
    "step1" : {
        "extravars" : [
            "IMAGE_FSTYPES:append = ' wic wic.bmap'"
        ]
    }
},
```

And to expand that, you need the `arch-qemu` entry from the `templates` section, which looks like:

```
"arch-qemu" : {
    "BUILDINFO" : true,
    "BUILDHISTORY" : true,
    "step1" : {
        "BBTARGETS" : "core-image-sato core-image-sato-dev core-image-sato-sdk_
↪core-image-minimal core-image-minimal-dev core-image-sato:do_populate_sdk",
        "SANITYTARGETS" : "core-image-minimal:do_testimage core-image-sato:do_
↪testimage core-image-sato-sdk:do_testimage core-image-sato:do_testsdk"
    },
    "step2" : {
        "SDKMACHINE" : "x86_64",
        "BBTARGETS" : "core-image-sato:do_populate_sdk core-image-minimal:do_
↪populate_sdk_ext core-image-sato:do_populate_sdk_ext",
        "SANITYTARGETS" : "core-image-sato:do_testsdk core-image-minimal:do_
↪testsdkext core-image-sato:do_testsdkext"
    },
    "step3" : {
        "BUILDHISTORY" : false,
        "EXTRACMDS" : ["${SCRIPTSDIR}/checkvnc; DISPLAY=:1 oe-selftest $
↪{HELPERSTMACHTARGS} -j 15"],
        "ADDLAYER" : ["${BUILDDIR}/../meta-selftest"]
    }
},
```

(continues on next page)

(continua dalla pagina precedente)

```
}
},
```

Combining these two entries you can see that `qemux86-64` is a three step build where `bitbake BBTARGETS` would be run, then `bitbake SANITYTARGETS` for each step; all for `MACHINE="qemux86-64"` but with differing `SDKMACHINE` settings. In step 1, an extra variable is added to the `build/conf/auto.conf` file to enable wic image generation.

While not every detail of this is covered here, you can see how the template mechanism allows quite complex configurations to be built up yet allows duplication and repetition to be kept to a minimum.

The different build targets are designed to allow for parallelization, so different machines are usually built in parallel, operations using the same machine and metadata are built sequentially, with the aim of trying to optimize build efficiency as much as possible.

The `config.json` file is processed by the scripts in the Helper repository in the `scripts` directory. The following section details how this works.

## 14.5.2 Autobuilder Target Execution Overview

For each given target in a build, the Autobuilder executes several steps. These are configured in `yocto-autobuilder2/builders.py` and roughly consist of:

1. *Run `clobberdir`.*

This cleans out any previous build. Old builds are left around to allow easier debugging of failed builds. For additional information, see [clobberdir](#).

2. *Obtain `yocto-autobuilder-helper`*

This step clones the [yocto-autobuilder-helper](#) git repository. This is necessary to avoid the requirement to maintain all the release or project-specific code within Buildbot. The branch chosen matches the release being built so we can support older releases and still make changes in newer ones.

3. *Write `layerinfo.json`*

This transfers data in the Buildbot UI when the build was configured to the Helper.

4. *Call `scripts/shared-repo-unpack`*

This is a call into the Helper scripts to set up a checkout of all the pieces this build might need. It might clone the [BitBake](#) repository, the [OpenEmbedded-Core \(OE-Core\)](#) repository as well as additional layers. It will use the data from the `layerinfo.json` file to help understand the configuration. It will also use a local cache of repositories to speed up the clone checkouts. For additional information, see [Autobuilder Clone Cache](#).

This step has two possible modes of operation. If the build is part of a parent build, it's possible that all the repositories needed may already be available, ready in a pre-prepared directory. An "a-quick" or "a-full" build would prepare this before starting the other sub-target builds. This is done for two reasons:

- the upstream may change during a build, for example, from a forced push and this ensures we have matching content for the whole build

- if 15 Workers all tried to pull the same data from the same repos, we can hit resource limits on upstream servers as they can think they are under some kind of network attack

This pre-prepared directory is shared among the Workers over NFS. If the build is an individual build and there is no "shared" directory available, it would clone from the cache and the upstreams as necessary. This is considered the fallback mode.

#### 5. *Call scripts/run-config*

This is another call into the Helper scripts where it's expected that the main functionality of this target will be executed.

## 14.5.3 Autobuilder Technology

The Autobuilder has Yocto Project-specific functionality to allow builds to operate with increased efficiency and speed.

### **clobberdir**

When deleting files, the Autobuilder uses `clobberdir`, which is a special script that moves files to a special location, rather than deleting them. Files in this location are deleted by an `rm` command, which is run under `ionice -c 3`. For example, the deletion only happens when there is idle IO capacity on the Worker. The Autobuilder Worker Janitor runs this deletion. See *Autobuilder Worker Janitor*.

### **Autobuilder Clone Cache**

Cloning repositories from scratch each time they are required was slow on the Autobuilder. We therefore have a stash of commonly used repositories pre-cloned on the Workers. Data is fetched from these during clones first, then "topped up" with later revisions from any upstream when necessary. The cache is maintained by the Autobuilder Worker Janitor. See *Autobuilder Worker Janitor*.

### **Autobuilder Worker Janitor**

This is a process running on each Worker that performs two basic operations, including background file deletion at IO idle (see "Run clobberdir" in *Autobuilder Target Execution Overview*) and maintenance of a cache of cloned repositories to improve the speed the system can checkout repositories.

### **Shared DL\_DIR**

The Workers are all connected over NFS which allows `DL_DIR` to be shared between them. This reduces network accesses from the system and allows the build to be sped up. The usage of the directory within the build system is designed to be able to be shared over NFS.

### **Shared SSTATE\_DIR**

The Workers are all connected over NFS which allows the `sstate` directory to be shared between them. This means once a Worker has built an artifact, all the others can benefit from it. The usage of the directory within the build system is designed for sharing over NFS.



## Shared Hash Equivalence Server

The Workers all use the same Hash Equivalence server, through a common definition for `BB_HASHSERVE`.

## Resulttool

All of the different tests run as part of the build generate output into `testresults.json` files. This allows us to determine which tests ran in a given build and their status. Additional information, such as failure logs or the time taken to run the tests, may also be included.

Resulttool is part of OpenEmbedded-Core and is used to manipulate these JSON results files. It has the ability to merge files together, display reports of the test results and compare different result files.

For details, see <https://wiki.yoctoproject.org/wiki/Resulttool>.

## 14.5.4 run-config Target Execution

The `scripts/run-config` execution is where most of the work within the Autobuilder happens. It runs through a number of steps; the first are general setup steps that are run once and include:

1. Set up any `buildtools` tarball if configured.
2. Call `buildhistory-init` if `buildhistory` is configured.

For each step that is configured in `config.json`, it will perform the following:

1. Add any layers that are specified using the `bitbake-layers add-layer` command (logging as stepXa)
2. Call the `scripts/setup-config` script to generate the necessary `build/conf/auto.conf` configuration file for the build
3. Run the `bitbake BBTARGETS` command (logging as stepXb)
4. Run the `bitbake SANITYTARGETS` command (logging as stepXc)
5. Run the `EXTRACMDS` command, which are run within the BitBake build environment (logging as stepXd)
6. Run the `EXTRAPLAINCMDS` command(s), which are run outside the BitBake build environment (logging as stepXd)
7. Remove any layers added in step 1 using the `bitbake-layers remove-layer` command (logging as stepXa)

Once the execution steps above complete, `run-config` executes a set of post-build steps, including:

1. Call `scripts/publish-artifacts` to collect any output which is to be saved from the build.
2. Call `scripts/collect-results` to collect any test results to be saved from the build.
3. Call `scripts/upload-error-reports` to send any error reports generated to the remote server.
4. Cleanup the *Build Directory* using `clobberdir` if the build was successful, else rename it to "build-renamed" for potential future debugging.

## 14.5.5 Deploying Yocto Autobuilder

The most up to date information about how to setup and deploy your own Autobuilder can be found in [README.md](#) in the [yocto-autobuilder2](#) repository.

We hope that people can use the [yocto-autobuilder2](#) code directly but it is inevitable that users will end up needing to heavily customize the [yocto-autobuilder-helper](#) repository, particularly the `config.json` file as they will want to define their own test matrix.

The Autobuilder supports two customization options:

- variable substitution
- overlaying configuration files

The standard `config.json` minimally attempts to allow substitution of the paths. The Helper script repository includes a `local-example.json` file to show how you could override these from a separate configuration file. Pass the following into the environment of the Autobuilder:

```
$ ABHELPER_JSON="config.json local-example.json"
```

As another example, you could also pass the following into the environment:

```
$ ABHELPER_JSON="config.json /some/location/local.json"
```

One issue users often run into is validation of the `config.json` files. A tip for minimizing issues from invalid JSON files is to use a `Git pre-commit-hook.sh` script to verify the JSON file before committing it. Create a symbolic link as follows:

```
$ ln -s ../../scripts/pre-commit-hook.sh .git/hooks/pre-commit
```

## 14.6 Reproducible Builds

### 14.6.1 How we define it

The Yocto Project defines reproducibility as where a given input build configuration will give the same binary output regardless of when it is built (now or in 5 years time), regardless of the path on the filesystem the build is run in, and regardless of the distro and tools on the underlying host system the build is running on.

### 14.6.2 Why it matters

The project aligns with the [Reproducible Builds project](#), which shares information about why reproducibility matters. The primary focus of the project is the ability to detect security issues being introduced. However, from a Yocto Project perspective, it is also hugely important that our builds are deterministic. When you build a given input set of metadata, we expect you to get consistent output. This has always been a key focus but, *since release 3.1 ("dunfell")*, it is now true down to the binary level including timestamps.

For example, at some point in the future life of a product, you find that you need to rebuild to add a security fix. If this happens, only the components that have been modified should change at the binary level. This would lead to much easier and clearer bounds on where validation is needed.

This also gives an additional benefit to the project builds themselves, our *Equivalenza degli Hash* for *Shared State* object reuse works much more effectively when the binary output remains the same.

#### **Nota**

We strongly advise you to make sure your project builds reproducibly before finalizing your production images. It would be too late if you only address this issue when the first updates are required.

### 14.6.3 How we implement it

There are many different aspects to build reproducibility, but some particular things we do within the build system to ensure reproducibility include:

- Adding mappings to the compiler options to ensure debug filepaths are mapped to consistent target compatible paths. This is done through the *DEBUG\_PREFIX\_MAP* variable which sets the `-fmacro-prefix-map` and `-fdebug-prefix-map` compiler options correctly to map to target paths.
- Being explicit about recipe dependencies and their configuration (no floating configure options or host dependencies creeping in). In particular this means making sure *PACKAGECONFIG* coverage covers configure options which may otherwise try and auto-detect host dependencies.
- Using recipe specific sysroots to isolate recipes so they only see their dependencies. These are visible as `recipe-sysroot` and `recipe-sysroot-native` directories within the *WORKDIR* of a given recipe and are populated only with the dependencies a recipe has.
- Build images from a reduced package set: only packages from recipes the image depends upon.
- Filtering the tools available from the host's *PATH* to only a specific set of tools, set using the *HOSTTOOLS* variable.

### 14.6.4 Can we prove the project is reproducible?

Yes, we can prove it and we regularly test this on the Autobuilder. At the time of writing (release 3.3, "hardknott"), *OpenEmbedded-Core (OE-Core)* is 100% reproducible for all its recipes (i.e. world builds) apart from the Go language and Ruby documentation packages. Unfortunately, the current implementation of the Go language has fundamental reproducibility problems as it always depends upon the paths it is built in.

#### **Nota**

Only BitBake and *OpenEmbedded-Core (OE-Core)* guarantee complete reproducibility. The moment you add another layer, this warranty is voided, because of additional configuration files, `bbappend` files, overridden classes, etc.

To run our automated selftest, as we use in our CI on the Autobuilder, you can run:

```
oe-selftest -r reproducible.ReproducibleTests.test_reproducible_builds
```

This defaults to including a `world` build so, if other layers are added, it would also run the tests for recipes in the additional layers. Different build targets can be defined using the *OEQA\_REPRODUCIBLE\_TEST\_TARGET* variable

in *build/conf/local.conf*. For example, running reproducibility tests for only the `python3-numpy` recipe can be done by setting:

```
OEQA_REPRODUCIBLE_TEST_TARGET = "python3-numpy"
```

in *build/conf/local.conf* before running the `oe-selftest` command shown above.

Reproducibility builds the target list twice. The first build will be run using *Shared State* if available, the second build explicitly disables *Shared State* except for recipes defined in the `OEQA_REPRODUCIBLE_TEST_SSTATE_TARGETS` variable, and builds on the specific host the build is running on. This means we can test reproducibility builds between different host distributions over time on the Autobuilder.

If `OEQA_DEBUGGING_SAVED_OUTPUT` is set, any differing packages will be saved here. The test is also able to run the `diffoscope` command on the output to generate HTML files showing the differences between the packages, to aid debugging. On the Autobuilder, these appear under <https://valkyrie.yocto.io/pub/repro-fail/> in the form `oe-reproducible + <date> + <random ID>`, e.g. `oe-reproducible-20200202-11m8o1th`.

The project's current reproducibility status can be seen at <https://www.yoctoproject.org/reproducible-build-results/>

You can also check the reproducibility status on the Autobuilder: <https://autobuilder.yoctoproject.org/valkyrie/#/builders/reproducible>.

## 14.6.5 How can I test my layer or recipes?

### With world build

Once again, you can run a world test using the `oe-selftest` command provided above. This functionality is implemented in `meta/lib/oeqa/selftest/cases/reproducible.py`.

### Subclassing the test

You could subclass the test and change `targets` to a different target.

You may also change `sstate_targets` which would allow you to "pre-cache" some set of recipes before the test, meaning they are excluded from reproducibility testing. As a practical example, you could set `sstate_targets` to `core-image-sato`, then setting `targets` to `core-image-sato-sdk` would run reproducibility tests only on the targets belonging only to `core-image-sato-sdk`.

### Using `OEQA_REPRODUCIBLE_TEST_*` variables

If you want to test the reproducibility of a set of recipes, you can define `OEQA_REPRODUCIBLE_TEST_LEAF_TARGETS`, in your *build/conf/local.conf*:

```
OEQA_REPRODUCIBLE_TEST_LEAF_TARGETS = "my-recipe"
```

This will test the reproducibility of `my-recipe` but will use the *Shared State* for most its dependencies (i.e. the ones explicitly listed in `DEPENDS`, which may not be all dependencies, c.f. `[depends] varflags`, `PACKAGE_DEPENDS` and other implementations).

You can have finer control on the test with:

- `OEQA_REPRODUCIBLE_TEST_TARGET`: lists recipes to be built,

- *OEQA\_REPRODUCIBLE\_TEST\_SSTATE\_TARGETS*: lists recipes that will be built using *Shared State*.

## 14.7 Yocto Project Compatible

### 14.7.1 Introduzione

After the introduction of layers to OpenEmbedded, it quickly became clear that while some layers were popular and worked well, others developed a reputation for being "problematic". Those were layers which didn't interoperate well with others and tended to assume they controlled all the aspects of the final output. This usually isn't intentional but happens because such layers are often created by developers with a particular focus (e.g. a company's *BSP*) whilst the end users have a different one (e.g. integrating that *BSP* into a product).

As a result of noticing such patterns and friction between layers, the project developed the "Yocto Project Compatible" badge program, allowing layers following the best known practises to be marked as being widely compatible with other ones. This takes the form of a set of "yes/no" binary answer questions where layers can declare if they meet the appropriate criteria. In the second version of the program, a script was added to make validation easier and clearer, the script is called `yocto-check-layer` and is available in *OpenEmbedded-Core (OE-Core)*.

See *Making Sure Your Layer is Compatible With Yocto Project* for details.

### 14.7.2 Benefits

*Il Modello a Layer di Yocto Project* is powerful and flexible: it gives users the ultimate power to change pretty much any aspect of the system but as with most things, power comes with responsibility. The Yocto Project would like to see people able to mix and match BSPs with distro configs or software stacks and be able to merge successfully. Over time, the project identified characteristics in layers that allow them to operate well together. "anti-patterns" were also found, preventing layers from working well together.

The intent of the compatibility program is simple: if the layer passes the compatibility tests, it is considered "well behaved" and should operate and cooperate well with other compatible layers.

The benefits of compatibility can be seen from multiple different user and member perspectives. From a hardware perspective (a *Layer BSP*), compatibility means the hardware can be used in many different products and use cases without impacting the software stacks being run with it. For a company developing a product, compatibility gives you a specification / standard you can require in a contract and then know it will have certain desired characteristics for interoperability. It also puts constraints on how invasive the code bases are into the rest of the system, meaning that multiple different separate hardware support layers can coexist (e.g. for multiple product lines from different hardware manufacturers). This can also make it easier for one or more parties to upgrade those system components for security purposes during the lifecycle of a product.

### 14.7.3 Validating a layer

The badges are available to members of the Yocto Project (as member benefit) and to open source projects run on a non-commercial basis. However, anyone can answer the questions and run the script.

The project encourages all layer maintainers to review the questions and the output from the script against their layer, as the way some layers are constructed often has unintended consequences. The questions and the script are designed to highlight known issues which are often easy to solve. This makes layers easier to use and therefore more popular.

It is intended that over time, the tests will evolve as new best known practices are identified, and as new interoperability issues are found, unnecessarily restricting layer interoperability. If anyone becomes aware of either type, please let the project know through the [technical calls](#), the [mailing lists](#) or through the [Technical Steering Committee \(TSC\)](#). The TSC is responsible for the technical criteria used by the program.

Layers are divided into three types:

- *"BSP" or "hardware support"* layers contain support for particular pieces of hardware. This includes kernel and boot loader configuration, and any recipes for firmware or kernel modules needed for the hardware. Such layers usually correspond to a *MACHINE* setting.
- *"distro" layers* defined as layers providing configuration options and settings such as the choice of init system, compiler and optimisation options, and configuration and choices of software components. This would usually correspond to a *DISTRO* setting.
- "software" layers are usually recipes. A layer might target a particular graphical UI or software stack component.

Here are key best practices the program tries to encourage:

- A layer should clearly show who maintains it, and who change submissions and bug reports should be sent to.
- Where multiple types of functionality are present, the layer should be internally divided into sublayers to separate these components. That's because some users may only need one of them and separability is a key best practice.
- Adding a layer to a build should not modify that build, unless the user changes a configuration setting to activate the layer, by selecting a *MACHINE*, a *DISTRO* or a *DISTRO\_FEATURES* setting.
- Layers should be documenting where they don't support normal "core" functionality such as where debug symbols are disabled or missing, where development headers and on-target library usage may not work or where functionality like the SDK/eSDK would not be expected to work.

The project does test the compatibility status of the core project layers on its *Autobuilder*.

The official form to submit compatibility requests with is at <https://www.yoctoproject.org/ecosystem/branding/compatible-registration/>. Applicants can display the badge they get when their application is successful.

---

The Yocto Project ®

[<docs@lists.yoctoproject.org>](mailto:docs@lists.yoctoproject.org)

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.

---

### Manuale Utente di BitBake

---

BitBake era originariamente parte del progetto OpenEmbedded. Si ispirava al sistema di gestione dei pacchetti Portage utilizzato dalla distribuzione Gentoo Linux. Nel 2004, il progetto OpenEmbedded fu suddiviso in due parti distinte:

- BitBake, un esecutore di task generico
- OpenEmbedded, un set di metadati utilizzato da BitBake

Oggi, BitBake è lo strumento di compilazione principale dei progetti basati su OpenEmbedded, come lo Yocto Project.

La documentazione di BitBake è disponibile [qui](#).





---

### Riferimento di Yocto Project Security

---

#### 16.1 Team di sicurezza

Il team di sicurezza di Yocto Project/OpenEmbedded coordina il lavoro sulle tematiche di sicurezza all'interno del progetto. Tutte le discussioni generali si svolgono pubblicamente. Il Security Team utilizza strumenti di comunicazione riservati esclusivamente per gestire le segnalazioni di vulnerabilità private prima della loro pubblicazione.

##### 16.1.1 Nomina del team di sicurezza

Lo Yocto Project Security Team è composto da almeno tre membri. Quando si rende necessario l'inserimento di nuovi membri, lo Yocto Project Technical Steering Committee (YP TSC) richiede candidature tramite canali pubblici, con una scadenza per la presentazione delle candidature. È possibile anche presentare autocandidature. Allo scadere del termine, l'YP TSC pubblica l'elenco dei candidati per raccogliere i commenti dei partecipanti al progetto e degli sviluppatori. I commenti possono essere inviati pubblicamente o privatamente all'YP TSC e all'OE TSC. I candidati vengono approvati sia dall'YP TSC che dall'OpenEmbedded Technical Steering Committee (OE TSC) e l'elenco definitivo dei membri del team viene reso pubblico. L'obiettivo è quello di avere presenti persone che rappresentino la leadership tecnica, le competenze in materia di sicurezza e infrastruttura, con un numero sufficiente di persone per garantire supporto/copertura, mantenendo al contempo l'elenco delle notifiche sufficientemente ristretto per minimizzare il rischio informativo e preservare la fiducia.

I membri dell'YP Security Team possono dimettersi in qualsiasi momento.

##### 16.1.2 Operazioni del Security Team

Il lavoro del Security Team potrebbe richiedere un elevato livello di riservatezza. I membri del team sono individui selezionati in base al merito e non rappresentano le aziende per cui lavorano. Non condividono informazioni riservate al di fuori del team e non accennano a embarghi in corso.

I membri del team possono coinvolgere esperti di dominio, se necessario. Tali esperti devono essere aggiunti solo a singoli problemi e attenersi agli stessi standard dell'YP Security Team.

Il team di sicurezza YP organizza riunioni e comunicazioni in base alle necessità.

Quando l'YP Security team riceve una segnalazione su una potenziale vulnerabilità di sicurezza, la analizza rapidamente e comunica il risultato al segnalatore. Potrebbe anche richiedere ulteriori informazioni.

Se il problema viene confermato e riguarda il codice gestito da YP, il team di sicurezza informa in via confidenziale i manutentori di tale codice e collabora con loro per preparare una soluzione.

Se il problema viene confermato e riguarda un progetto upstream, il team di sicurezza YP informa il progetto. Di solito, il progetto upstream analizza nuovamente il problema. Se lo ritiene un vero problema di sicurezza nel proprio software, sviluppa e rilascia una soluzione seguendo la propria politica di sicurezza. Potrebbe voler coinvolgere anche il segnalatore originale. A volte è necessario coordinarsi per la gestione delle patch, il backporting delle patch, ecc., o semplicemente per comprendere il problema o le sue cause.

La politica di sicurezza del progetto upstream potrebbe includere una notifica preventiva alle distribuzioni Linux o ad altri importanti progetti downstream per discutere una divulgazione coordinata. Queste mailing list sono normalmente private.

Quando il progetto upstream rilascia una versione con la correzione, è sua responsabilità contattare una CVE Numbering Authority (CNA) appropriata, come [Mitre](#), per ottenere l'assegnazione di un numero CVE e la pubblicazione del record CVE.

Quando la correzione è disponibile pubblicamente, il membro del team di sicurezza di YP o il manutentore del pacchetto invia le patch al codice sorgente di YP, seguendo le procedure standard, inclusa la revisione pubblica del codice.

### Se un progetto upstream non risponde tempestivamente

Se un progetto upstream non risolve il problema entro un tempo ragionevole, il Security Team di Yocto contatterà altre parti interessate (di solito altre distribuzioni) nella community e cercherà insieme di risolvere la vulnerabilità il più rapidamente possibile.

Lo Yocto Project Security aderisce di default alla politica di divulgazione di 90 giorni. Se necessario, è possibile prolungare il periodo di embargo.

### Gestione degli embarghi multi-progetto

In rari casi, un grave problema di sicurezza può interessare più progetti. Potrebbe trattarsi di numerosi progetti che presentano un problema simile a causa della progettazione, del modello di codifica o del riutilizzo dello stesso codice (un esempio di questa situazione è [CVE-2023-44487](#), in cui più server web condividono una vulnerabilità di progettazione). Potrebbe anche trattarsi di un problema di alto profilo in una libreria di uso comune (come OpenSSL). In questi casi, il progetto che viene a conoscenza del problema per primo potrebbe decidere di notificare in via confidenziale gli altri progetti interessati, in modo che possano sviluppare una soluzione sincronizzata. Potrebbe anche trattarsi del progetto interessato che informa le principali distribuzioni affinché rilascino l'aggiornamento simultaneamente.

Tali notifiche avvengono tramite canali riservati e non pubblici. In genere, il progetto che avvia l'"embargo" notifica direttamente un numero selezionato di persone di ciascun progetto, incluso un sottoinsieme del team di sicurezza. Quando Yocto Project fa parte di questo gruppo notificato, gli sviluppatori preparano le correzioni su un'infrastruttura

separata e le testano. Potrebbero anche includere altri sviluppatori ed esperti del settore che possono contribuire alla risoluzione del problema e a eventuali regressioni. Una volta terminato l'embargo, inviano una patch alla mailing list pubblica competente e inizia il normale processo di revisione.

### 16.1.3 Membri del Team di Sicurezza

Per comunicazioni sicure, si prega di inviare i messaggi crittografati utilizzando le chiavi GPG. Ricordate che le intestazioni dei messaggi non sono crittografate, quindi non includete informazioni sensibili nell'oggetto.

- Ross Burton: <ross [at] burtonini [dot] com> [Chiave pubblica](#)
- Michael Halstead: <mhalstead [at] linuxfoundation [dot] org> [Chiave pubblica](#) o [Chiave pubblica](#)
- Richard Purdie: <richard.purdie [at] linuxfoundation [dot] org> [Chiave pubblica](#)
- Marta Rybczynska: <marta DOT rybczynska [at] ygreky [dot] com> [Chiave pubblica](#)
- Paul Barker <paul [at] pbarker [dot] dev> [Chiave pubblica](#)

## 16.2 Segnalazione di Vulnerabilità

Yocto Project e OpenEmbedded sono progetti open source, basati sulla community, utilizzati in numerosi prodotti. Essi integrano diversi altri progetti open source e devono gestire problematiche e pratiche di sicurezza sia interne (nel codice gestito da entrambi i progetti) che esterne (gestite da altri progetti e organizzazioni).

Questo manuale raccoglie informazioni relative alla sicurezza dell'intero ecosistema. Include informazioni su come segnalare una potenziale vulnerabilità, sul funzionamento del team di sicurezza di YP e su come contribuire al codice correlato. È stato scritto per essere utile sia ai ricercatori di sicurezza che agli sviluppatori YP.

### 16.2.1 Come segnalare una potenziale vulnerabilità di sicurezza?

Per segnalare un problema pubblico (ad esempio, uno con un numero CVE rilasciato), segnalarlo utilizzando il [Security Bugzilla](#).

Se si riscontra un problema non ancora rilasciato o se si tratta di un problema urgente, inviare un messaggio security AT yoctoproject DOT org, includendo il maggior numero possibile di dettagli: il layer o il modulo software interessato, la ricetta e la sua versione, ed eventuali esempi di codice, se disponibili. Questa mailing list è monitorata dal team di Yocto Project Security.

Per ogni layer, si possono anche cercare istruzioni specifiche (se presenti) per la segnalazione di potenziali problemi di sicurezza nel file `SECURITY.md` nella directory principale del repository. Le istruzioni su come e dove inviare una patch sono generalmente disponibili nel file `README.md`. Se questa è la prima patch per Yocto Project/OpenEmbedded, si dovrebbe consultare la sezione "*Preparazione delle Modifiche per l'Invio*".

### Branch mantenuti con correzioni di sicurezza

Consultare la documentazione [Processo di rilascio](#) per i dettagli relativi alle politiche e alla manutenzione dei branch stabili.

La pagina [Releases](#) contiene un elenco di tutti i rilasci di Yocto Project, suddivisi in rilasci correnti e precedenti. I rilasci precedenti non sono più attivamente mantenuti con patch di sicurezza, ma le patch ben testate possono ancora essere accettate per la risoluzione di problemi significativi.

## Discussioni relative alla sicurezza in Yocto Project

Abbiamo creato due mailing list/email relative alla sicurezza:

- Public Mailing List: `yocto [dash] security [at] yoctoproject[dot] org`

Questa è una mailing list pubblica a cui chiunque può iscriversi. Questa lista è aperta per discutere di problemi/patch di sicurezza pubblici e iniziative relative alla sicurezza. Per ulteriori informazioni, incluse quelle relative all'iscrizione, consultare la pagina informativa della mailing list [yocto-security mailing list info page](#).

Questa lista richiede l'approvazione di un moderatore per la pubblicazione di nuovi argomenti, al fine di evitare la pubblicazione accidentale di segnalazioni di sicurezza private.

- Yocto Project Security Team: `security [at] yoctoproject [dot] org`

Questo indirizzo email è dedicato alla segnalazione di potenziali vulnerabilità non ancora pubblicate. Le email inviate a questo indirizzo vengono inoltrate ai membri di Yocto Project Security Team.

## Cosa fare in caso di vulnerabilità di sicurezza

Se si riscontra una falla di sicurezza: un crash, una fuga di informazioni o qualsiasi altra vulnerabilità che, se sfruttata, possa avere un impatto sulla sicurezza di qualsiasi software open source sviluppato o utilizzato da Yocto Project, si prega di segnalarla al Yocto Project Security Team. Se si preferisce contattare direttamente il progetto upstream, si prega di inviare una copia anche al team di sicurezza di Yocto Project. Se si ritiene che si tratti di informazioni altamente sensibili, segnalare la vulnerabilità in modo sicuro, ad esempio crittografando l'e-mail e inviandola alla lista privata. In questo modo si evita che la vulnerabilità venga divulgata e sfruttata prima che sia stata elaborata una risposta o una soluzione.

---

The Yocto Project ®

[<docs@lists.yoctoproject.org>](mailto:docs@lists.yoctoproject.org)

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo `docs@lists.yoctoproject.org` o di accedere su [Libera Chat](#) al canale `#yocto`.

---

## Informazioni sulla Release

---

Each document in this chapter provides release notes and information about how to move to one release of the Yocto Project from the previous one.

### 17.1 Introduzione

This guide provides a list of the backwards-incompatible changes you might need to adapt to in your existing Yocto Project configuration when upgrading to a new release.

If you are upgrading over multiple releases, you will need to follow the sections from the version following the one you were previously using up to the new version you are upgrading to.

#### 17.1.1 General Migration Considerations

Some considerations are not tied to a specific Yocto Project release. This section presents information you should consider when migrating to any new Yocto Project release.

- *Dealing with Customized Recipes:*

Issues could arise if you take older recipes that contain customizations and simply copy them forward expecting them to work after you migrate to new Yocto Project metadata. For example, suppose you have a recipe in your layer that is a customized version of a core recipe copied from the earlier release, rather than through the use of an append file. When you migrate to a newer version of Yocto Project, the metadata (e.g. perhaps an include file used by the recipe) could have changed in a way that would break the build. Say, for example, a function is removed from an include file and the customized recipe tries to call that function.

You could "forward-port" all your customizations in your recipe so that everything works for the new release. However, this is not the optimal solution as you would have to repeat this process with each new release if changes occur that give rise to problems.

The better solution (where practical) is to use append files (`*.bbappend`) to capture any customizations you want to make to a recipe. Doing so isolates your changes from the main recipe, making them much more manageable. However, sometimes it is not practical to use an append file. A good example of this is when introducing a newer or older version of a recipe in another layer.

- *Updating Append Files:*

Since append (`.bbappend`) files generally only contain your customizations, they often do not need to be adjusted for new releases. However, if the append file is specific to a particular version of the recipe (i.e. its name does not use the `%` wildcard) and the version of the recipe to which it is appending has changed, then you will at a minimum need to rename the append file to match the name of the recipe file. A mismatch between an append file and its corresponding recipe file (`.bb`) will trigger an error during parsing.

Depending on the type of customization the append file applies, other incompatibilities might occur when you upgrade. For example, if your append file applies a patch and the recipe to which it is appending is updated to a newer version, the patch might no longer apply. If this is the case and assuming the patch is still needed, you must modify the patch file so that it does apply.

#### **Suggerimento**

You can list all append files used in your configuration by running:

```
bitbake-layers show-append
```

- *Checking Image / SDK Changes:*

The `buildhistory` class can be used if you wish to check the impact of changes to images / SDKs across the migration (e.g. added/removed packages, added/removed files, size changes etc.). To do this, follow these steps:

1. Enable `buildhistory` before the migration
2. Run a pre-migration build
3. Capture the `buildhistory` output (as specified by `BUILDHISTORY_DIR`) and ensure it is preserved for subsequent builds. How you would do this depends on how you are running your builds - if you are doing this all on one workstation in the same `Build Directory` you may not need to do anything other than not deleting the `buildhistory` output directory. For builds in a pipeline it may be more complicated.
4. Set a tag in the `buildhistory` output (which is a git repository) before migration, to make the commit from the pre-migration build easy to find as you may end up running multiple builds during the migration.
5. Perform the migration
6. Run a build

7. Check the output changes between the previously set tag and HEAD in the *buildhistory* output using `git diff` or `buildhistory-diff`.

For more information on using *buildhistory*, see *Maintaining Build Output Quality with buildhistory*.

## 17.2 Release 6.1 (blacksail)

### 17.2.1 Release notes for 6.1 (blacksail)

This document lists new features and enhancements for the Yocto Project 6.1 Release (codename "blacksail"). For a list of breaking changes and migration guides, see the *Migration notes for 6.1 (blacksail)* section.

#### New Features / Enhancements in 6.1

- Linux kernel 7.2, gcc 16.2, glibc 2.44, LLVM 23.1.1, and over 300 other recipe upgrades
- Minimum Python version required on the host: 3.9.
- Kernel-related changes:
  - *kernel-module-split*: Return list of values in `extract_modinfo` (43da9b9)
  - *kernel*: Disable module tarball deployment (`MODULE_TARBALL_DEPLOY`) by default (f51d48c)
  - *linux-yocto*: Remove CVE exclusion list as *sbom-cve-check* does this itself (596ad6c)
  - *kernel-fit-image*:
    - \* Validate key files expected by `mkimage` for the selected algorithm (7570ab5)
    - \* Do not include `kernel` property in DTBO configuration sub-nodes (06ed340)
    - \* Fix operation with `KERNEL_DTBVENDORED` set to "1" (4297b94)
    - \* Add `KERNEL_DTBVENDORED` support for `FIT_CONF_DEFAULT_DTB` (3bceb2d)
    - \* Make kernel entry point and load address optional (54c4b48)
    - \* Avoid shadowing `os` `stdlib` import (fe1b5a0)
    - \* Introduce `FIT_OS` variable to override 'os' field (dc00e83)
    - \* Reference the boot script as "script" (6bb0775)
    - \* Skip sign key check for PKCS #11 URI (b606b71)
    - \* Don't add configuration hash node when signing is enabled (7346ffe)
  - *kernel-arch*: Add *Clang* toolchain support (928d819)
  - *kernel-arch*: Fall back to GNU `ld` unless `ld-is-ld` is in `DISTRO_FEATURES` (f92bfb5)
  - *kernel-yocto*: Set `CLANG_FLAGS` for kernel config checks when using *Clang* (e88ee79)
  - *linux-yocto-dev*: Enable BSP config audit reporting (through `KCONF_BSP_AUDIT_LEVEL`) (c98e839)
  - *kernel-devsrc*: Install sources required for BPF host tools (cf5b627)
  - *kernel-yocto-rust*: Add *Clang* toolchain check for `riscv64` (2b22849)

- `lib/oe/kernel_module.py`: Re-sign kernel modules after package stripping process ([a608d10](#))
- *kernel-module-split*: Don't re-sign compressed kernel modules ([3483d02](#))
- New core recipes:
  - `python3-vcs-versioning`: Added as a new dependency of the `python3-setuptools-scm` recipe ([507bb52](#))
  - `cgo-helloworld`: A Go example recipe with `cgo` enabled ([204e4f7](#))
  - `jansson`: Add a recipe from `meta-oe`, as it is a new hard dependency of the `igt-gpu-tools` recipe ([2b6e7d0](#))
  - `packagegroup-core-buildessential-rust`: A *packagegroup* to provide the on-target dependencies required for building *Rust*-based kernel modules, including the *Rust* toolchain, `bindgen`, and `libclang` ([500b45f](#))
  - `nativesdk-packagegroup-sdk-host-rust`: Similar to `packagegroup-core-buildessential-rust` but for building *Rust*-based kernel modules in the SDK ([a05c097](#))
  - `nativesdk-packagegroup-sdk-host-clang`: *nativesdk packagegroup* providing the *Clang*, `lld`, and `llvm-bin` dependencies needed to build external/out-of-tree modules in the SDK using the LLVM/Clang toolchain ([2b1db6e](#))
  - `gststreamer1.0-plugins-rs`: GStreamer Rust plugins ([3a2b032](#))
  - `rust-source`: Recipe that fetches, unpacks, and patches the `rustc` source tree into a "work-shared" location ([395fe16](#))
  - `libzip`: Added because it is a dependency of various tools ([f17e875](#))
  - `mesa-libclc`: New recipe for forking `libclc` for `Rustic1` purposes in Mesa ([956aaf3](#))
  - `libtracefs`: Added as `powertop` version 2.16 requires it ([3c3f227](#))
  - `libfaketime`: Used for reproducibility testing ([f3a4faa](#))
  - `python3-tomlkit`: New dependency of `hatchling` ([46d3b26](#))
- New core classes:
  - *python\_uv\_build*: Used to build Python recipes with `uv_build`, a slimmed down version of `uv` ([c535a9f](#))
  - *upstream-stable-release-point*: Helper class for setting the `UPSTREAM_STABLE_RELEASE_REGEX` variable with `STABLE_VERSION_PARTS` ([a1e069d](#))
  - *python\_pbr*: Used to build Python recipes with the *Python Build Reasonableness* backend ([b9f3b36](#))
- New variables:
  - `UBOOT_FIT_CONF_DESC` allows configuring the description property of the configuration node of a U-Boot FIT image ([df16e4a](#))
  - `KERNEL_TOOLCHAIN`: Allows specifying the toolchain to use to build the Linux kernel ([0e3756e](#))
  - `FIT_OS`: Controls the `os` field of the FIT image built with the *kernel-fit-image* class ([dc00e83](#))
  - `CARGO_PROFILE`: Allows selecting the *cargo* profile to use (`--profile`) ([d4de7d0](#))



- *OpenEmbedded-Core (OE-Core)* library changes:
  - oe/lsb: Only read /etc/os-release (1331c5f)
  - oe/utils: Drop all\_distro\_features() (28d32a9)
- Global configuration changes:
  - bitbake.conf:
    - \* Define a new `firmwaredir` variable (which by default points to `/lib/firmware`). This variable was adopted in several recipes to replace `${nonarch_base_libdir}/firmware` (2b75c7b)
    - \* Drop `openc1` from `DISTRO_FEATURES_FILTER_NATIVE` and `DISTRO_FEATURES_FILTER_NATIVESDK` (f810998)
  - *useradd*\*: Add support for the `USERMOD_PARAM` variable, acting as a replacement of the `GROUPMEMS_PARAM` variable (b8da733, cec67e2)  
  
Show a deprecation warning if `GROUPMEMS_PARAM` is used (06f48de)
  - *useradd*\*: Switch from `--root` to `--prefix` option (a7b846b)
- BitBake changes:
  - The `git-make-shallow` utility script was dropped along with its test cases. It was replaced by Git native shallow fetches 0223ec6
  - Replace `codegen` with `ast.unparse()` (76dd6d6)
  - After the removal of the previous obsolete `bb.fetch` module, the `bb.fetch2` module was renamed to `bb.fetch`. A warning will be printed if `bb.fetch2` is used in layers (34ea7cb)
  - `fetch/git`:
    - \* Fix leaking of temporary directory (c7ebe03)
    - \* Fix trailing slash in clone command causing double slash in alternates (797b0a3)
    - \* Accept SHA256 revisions (707ba7e)
  - Unpack RPMs with `--no-absolute-filenames` (1b1a715)
  - `tinfoil`:
    - \* Only allow one process progress bar at once (d6bc0e5)
    - \* Add a prepared task runner, to execute a single recipe task and nothing else (280a3b3)
  - `knotty`: Show elapsed time on the task progress bar (b8dfa35)
  - `bitbake-setup`:
    - \* Add a "notes" item to `bitbake-setup` configuration files which create a "conf-notes.txt" file in the *Build Directory* (020a5ba)
    - \* Add a `--version` option (0e39aca)
    - \* Add PyPI packaging for `bitbake-setup`, allowing to install the tool with `pip` (6b51b93)
    - \* Use the *BitBake* built-in fetcher for buildtools installer download (e8d531c)

- \* `default-registry`: Use the [core/yocto/monitor-disk-space](#) fragment by default (975b322)
  - \* Print a note about `fetcher` log if something fails there (3860fab)
- `lib`: Drop `pyinotify`, as it wasn't used by [BitBake](#) anymore (d20e7dc)
- `lib`: Rename `fetch2` as `fetch` and invert compatibility shim to make `bb.fetch2` equal to `bb.fetch` (34ea7cb)
- `fetch`: Switch to shared locking for read accesses (e8f8ab6)
- `fetch/crate`: Support user-defined protocols (22a993a)
- `fetch`: Export `AWS_SHARED_CREDENTIALS_FILE` for S3 fetches, allowing to use a credential file different than `~/.aws/credentials` (0d6aa2b)
- `fetch/{npm, npmsw}`: Re-enable fetchers now that checksums come from [SRC\\_URI](#), and restore the `fetcher`'s test coverage (9e45e00, f7608f3)
- `fetch/wget`:
  - \* Handle long filenames correctly (da1fcdf)
  - \* Reuse cached HTTPS connections (2c236d8)
  - \* Cache SSL context instead of recreating every time (625b25a)
- `fetch/git-sm`: Store the original URL data to fix relative `git-sm://` paths (5887225)
- Add `pyproject.toml` and `vendor.txt` for vendoring (70b54fd)
- `data`: Return a list from `exported_vars()` (c870f5b)
- `asynccrpc`: Add Task Group (4fc36e6)
- `hashserv`:
  - \* Client: Add asynchronous streaming API (544d9f1)
  - \* Server: Add queued streaming API (9e0f064)
- **SPDX-related changes:**
  - Add SHA 512 support (383a5a6)
  - Add custom annotations to recipe packages (e5a4a7d)
  - `common-licenses`: Add SPDX License Exceptions (9c8d126)
  - `lib/oe`: Add SPDX license library (51c7930)
  - `lib/oe/license`: Rework package licenses matching (e3c5cb7)
  - `lib/oe/spdx30_tasks`: Fix image deploy dir (fe3a721)
- **[sbom-cve-check](#)-related changes:**
  - `sbom-cve-check` recipe: Enable offline mode (db2e0fd)
- **Packaging changes:**
  - `package_manager/ipk`: Skip checksums for unsigned local feeds (3f50b04)

- *package\_rpm*: Drop external dependency generator to support RPM 6 (093ae99)
- *libarchive*: Add RPM format reader to support RPM 6 (8401bac)
- No longer modify paths in `save_debugsources_info()` (b567c2f)
- QEMU / *runqemu* changes:
  - *runqemu-export-rootfs*: Set *PSEUDO\_INCLUDE\_PATHS* for *unfsd* (76b8b83)
  - *runqemu-extract-sdk*: Refactor in Python (78c176d)
  - *qemu*: Set the compilation progress bar flag (21994d6)
  - *qemu*: Add *ppc64le* support to *COMPATIBLE\_HOST* (77a329d)
  - *python3-qemu-qmp*: Added as a new dependency of QEMU (5babf4e)
- Documentation changes:
  - New document on *shared state signing*
  - New document on *setting up a shared state mirror*
  - New document on how security is handled in builds: *Sicurezza del Processo di Build*
- Go changes:
  - *go-vendor*: Remove vendor symlink (d3cbc28)
- Testing-related changes:
  - *ptest* support was added for the following recipes:
    - \* *go* (9ca4140)
    - \* *libatomic-ops* (d899b7f)
    - \* *libcap* (bfc0a65)
    - \* *libxslt* (fa4328b)
    - \* *python3-certifi* (0aa251f)
    - \* *python3-pyopenssl* (3fdfff9)
    - \* *python3-vcs-versioning* (90c8bc1)
    - \* *wget* (bb24e39)
    - \* *zstd* (f3e3ccb)
  - *meta-selftest*: Add a *usegroup-deponly* recipe to test *USERADD\_DEPENDS* only (36eac58)
  - *python3*: Use a *SKIPPED\_TESTS* variable instead of test skip patches (a8b2baa)
  - *oeqa/oelible*: Add *runcmd* tests (b364c44)
  - *oeqa/selftest/pkgdata*: Add a test for variable consistency in *multilib\** (b937278)
  - *oeqa/selftest/kernelmodulesplit*: Test cross-recipe kernel module dependencies (6ca1f21)
  - *oe-selftest: kernel-fit-image*: Add tests for *KERNEL\_DTBVENDORED* (de2e11e)

- *testimage*: Handle bootlog variants on failed QEMU tests (7a65969)
- oeqa/selftest: Add *go-vendor* selftest suite (79d251a)
- oeqa/selftest/clang: Add selftests for Clang/LLVM/LLD test suites (8e7a293)
- oe-selftest: devtool: Add test for add/finish workflow (36472a7)
- devtool-related changes:
  - Disable GPG signing when setting up source tree repos (b5c84b0)
  - upgrade command: Extract changelog between versions (ddd54d6)
  - Fix finish/update-recipe for recipes using *AUTOREV* (ae7be93)
  - Fix update-recipe/finish --initial-rev override (62abb60)
  - Guess srcrev update mode for git-sm:// recipes too (9307c37)
  - upgrade: Ignore changelogs from 3rd party (1c9d4bb)
  - deploy-target: Fix running strip under pseudo (a48a731)
  - ide-sdk:
    - \* Add *LLDB* support for *Clang* toolchain (e81d897)
    - \* Default to all modified recipes (4c1c0ff)
    - \* Auto-write image debug settings to bbappend (929a8c1)
    - \* Support runqemu slirp (5cc15ec)
    - \* Support NFS rootfs (4ab284a)
    - \* Add clangd support for VSCode IntelliSense (10a0a09)
    - \* Support clangd for non-clang toolchain recipes (da9ac67)
    - \* Format C/C++ with clangd when .clang-format is present (5c13e48)
    - \* Support LLDB ATTACH mode (6a4227b)
    - \* Allow --ide to select multiple plugins (8aa5c03)
  - Fix file copy on finish --force (b8fda5d)
  - deploy-target: Add --package/--file-glob filters (cf6d07f)
  - deploy: Make pseudo calls independent of bitbake.conf (462019b)
  - deploy: Allow deploying directly into a local rootfs directory (763accb)
- Utility script changes:
  - scripts/cve-json-to-text.py: Simplify getopt argument parsing (a92dfe5)
  - upgrade command: Add a --stable option (1e86aa0)
  - oe-pkgdata-util: Fix empty runtime-rprovides directory handling (678c1c2, dbca656)
  - recipeutils: Add optional stable\_upgrade parameter to get\_recipe\_upgrade\_status, to add the possibility of doing stable version upgrades of recipes (1ed8fdd)

- `scripts/pull-spdx-licenses.py`: Add exceptions to the script that updates the SPDX license files (4190cdd)
- `install-buildtools`:
  - \* Auto-discover environment setup script via glob (1105378)
  - \* Add a `--local-file` option (e160ff4)
- `scripts/contrib`: Add `reuse-get-license.py`, a script that extracts the `LICENSE` and `LIC_FILES_CHKSUM` for projects that use `reuse` (8ec5b74)
- `scripts/contrib`: Add helper to report and fix missing `SRC_URI` ; tag= parameters (d9a75fa)
- `resulttool`: Add support for ptests results for both *Musl* and *Glibc* (c0508fb)
- `scripts/oe-depends-dot`: Give the `dotfile` argument a sensible default (88620a3)
- `sstate-cache-management.py`: Also check the `SSTATE_DIR` environment variable for `--cache-dir` (ad44f5e)
- Clang/LLVM-related changes:
  - `clang`: Enable cmake flags for llvm, clang, lld tests (c926c4f)
- Patchtest-related changes:
- *insane* / *sanity* classes-related changes:
  - Add a check that `SOURCE_MIRROR_URL` is defined when *own-mirrors* is used (6d989b9)
  - Add a check for build host `HOME` directory in packaged files (81bbe42)
  - Allow exceptions in `buildpaths` `HOME` checks (ee29a91)
  - *sanity*: Warn on *Cargo* config files outside of the build tree (77516d3)
  - Increase shebang size limit (c205e77)
  - Improve `HOME` checks exceptions (f6b9494)
- Security changes:
- *sbom-cve-check*-related changes:
- New *PACKAGECONFIG* options for individual recipes:
  - `curl`: `libpsl`, `libssh`
  - `dhcpcd`: `seccomp`
  - `ethtool`: `pretty-dump`
  - `ffmpeg`: `libdav1d`
  - `iproute2`: `dcb`, `dp11`
  - `libical`: `introspection`, `vala`
  - `libportal`: `gtk4`
  - `librsvg`: `avif`, `gdkpixbuf`

- p11-kit: systemd, trust
- pciutils: dns, shared
- perf: bpf-skel, llvm
- seatd: manpages
- strace: libdw
- vim: desktop
- webkitgtk: bubblewrap, librice, webrtc
- wpa-supPLICant: suiteb, mbo, wnm
- systemd-related changes:
  - systemd-tools-native: Add systemd-hwdb (2a7c2dd)
  - systemd: Enable coredump in *PACKAGECONFIG* by default (1086a56)
- U-Boot-related changes:
  - Add support for *Clang* toolchain (3214211)
  - *uboot-sign*: List the TEE loadable behind U-Boot (a9a20a0)
- Busybox-related changes:
  - fdisk: Enable GPT support (d0914b8)
  - Enable xxd (2852025)
  - Enable findfs for initramfs LABEL support (c2b681e)
- initramfs-framework-related changes:
  - overlayroot: Use switch\_root instead of chroot (848c368)
  - Add opt-in root-only udev trigger (d3a196f)
  - Support LABEL with root-only udev trigger (fda394c)
  - Avoid external commands in rootfs resolution (d6e8e72)
  - Allow opting out of efivarfs mount (9147744)
- Miscellaneous changes:
  - pulseaudio: Split pactl into a dedicated client subpackage (31dd308)
  - u-boot-tools: Add dependency on libyaml for dt-schema validation (02e09e0)
  - p11-kit: Rewrite packaging to provide additional p11-kit-modules and p11-kit-remote packages (7511a86)
  - harfbuzz: Improve packaging (fb39870)
  - *sstate*: Detect broken shared state paths containing *TMPDIR* (907af8f)
  - gcr: Package the ssh-agent into a separate package (c957909)
  - glibc: Disable automatic libatomic linking (677f0ac)

- *uboot-sign*: Sign SPL FIT into a copy of the SPL DTB (79584fe)
- *archiver*: Properly remove artifacts when configuration changes (4b0ac92)
- *wget*: Disable NTLM support (4eb7e98)
- *vex*: Drop obsolete conflict check with `cve-check` class (ddb00a3)
- *toaster*: Support layers that are not Git repositories (3fb96cc)
- `classes/meson`: Use *ninja* explicitly when compiling (9e1513b)
- `webkitgtk`: Allow using *Clang* to compile for arm target (7702381)
- *report-error*: Add `site.conf/toolcfg.conf` into error report (40ca5fc)
- *cml1*: Use `KCONFIG_CONFIG_ROOTDIR` in `savedefconfig` (4696450)
- *uki*: Make *initramfs* optional (909d3ba)
- `cpan_build`: Disable `.packlist` and HTML doc (3c2bb7b)
- *useradd*\*: Drop `groupmems` from *sysroot* setup, as `groupmems` was removed from *shadow* version 4.20.0 (de0bf57)
- *image\_types*: Make `oe_mkext234fs` reproducible (8d1d548)
- *pypi*: Only set `downloadprefix` in `SRC_URI` if needed (be391d8)

## Known Issues in 6.1

N/A

## Recipe License changes in 6.1

The following changes have been made to the *LICENSE* values set by recipes:

| Recipe(s)           | Previous value                                                                               | New value                                                                                                                                                                                                                                                                  |
|---------------------|----------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| erofs-utils         | GPL-2.0-or-later                                                                             | MIT AND (GPL-2.0-or-later OR MIT)                                                                                                                                                                                                                                          |
| git                 | GPL-2.0-only AND GPL-2.0-or-later AND BSD-3-Clause AND MIT AND BSL-1.0 AND LGPL-2.1-or-later | GPL-2.0-only AND GPL-2.0-or-later AND BSD-3-Clause AND MIT AND LGPL-2.1-or-later                                                                                                                                                                                           |
| fmt                 | MIT                                                                                          | MIT-with-fmt-exception                                                                                                                                                                                                                                                     |
| vulkan-headers      | Apache-2.0 AND MIT                                                                           | Apache-2.0 AND MIT AND (Apache-2.0 OR MIT)                                                                                                                                                                                                                                 |
| vulkan-validation-l | Apache-2.0 AND BSL-1.0 AND MIT                                                               | Apache-2.0 AND BSL-1.0 AND MIT AND BSD-2-Clause AND (Apache-2.0 WITH LLVM-exception)                                                                                                                                                                                       |
| lttng-tools         | GPL-2.0-only AND LGPL-2.1-only                                                               | BSD-2-Clause AND BSD-3-Clause AND BSL-1.0 AND CC0-1.0 AND CC-BY-SA-4.0 AND FSFAP AND GPL-2.0-only AND GPL-2.0-or-later AND GPL-2.0-or-later WITH Autoconf-exception-2.0 AND GPL-2.0-or-later WITH Autoconf-exception-macro AND LGPL-2.1-only AND LGPL-2.1-or-later AND MIT |

## Security Fixes in 6.1

The following CVEs have been fixed:

| Recipe                | CVE IDs                                                                                                                                                                                                                        |
|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| acl                   | CVE-2026-54369, CVE-2026-54370                                                                                                                                                                                                 |
| alsa-lib              | CVE-2026-90781                                                                                                                                                                                                                 |
| attr                  | CVE-2026-54371                                                                                                                                                                                                                 |
| avahi                 | CVE-2025-59529                                                                                                                                                                                                                 |
| bind                  | CVE-2026-19033, CVE-2026-19662, CVE-2026-19666, CVE-2026-19667, CVE-2026-19668, CVE-2026-19941, CVE-2026-75029, CVE-2026-76163, CVE-2026-77119, CVE-2026-77692, CVE-2026-78301, CVE-2026-80274, CVE-2026-81563, CVE-2026-81736 |
| binutils              | CVE-2026-6844, CVE-2026-6845                                                                                                                                                                                                   |
| binutils-cross-x86_64 | CVE-2026-6844, CVE-2026-6845                                                                                                                                                                                                   |
| binutils-testsuite    | CVE-2026-6844, CVE-2026-6845                                                                                                                                                                                                   |
| bison                 | CVE-2026-56390                                                                                                                                                                                                                 |
| bluez5                | CVE-2026-19774                                                                                                                                                                                                                 |

continues on next page



Tabella 1 – continua dalla pagina precedente

| Recipe          | CVE IDs                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| busybox         | CVE-2026-38752, CVE-2026-38753, CVE-2026-38755                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| cairo           | CVE-2025-50422                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| coreutils       | CVE-2026-56392                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| cryptodev-linux | CVE-2026-28529                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| cups            | CVE-2024-47850                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| curl            | CVE-2026-7009, CVE-2026-8458, CVE-2026-8925, CVE-2026-8926, CVE-2026-9079, CVE-2026-9080, CVE-2026-9545, CVE-2026-9546, CVE-2026-11564, CVE-2026-11856, CVE-2026-13608, CVE-2026-18924, CVE-2026-19931, CVE-2026-80229, CVE-2026-80230, CVE-2026-80231, CVE-2026-80255, CVE-2026-82208, CVE-2026-82209                                                                                                                                                                                                         |
| epiphany        | CVE-2026-18487                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| expat           | CVE-2025-66382, CVE-2026-50219, CVE-2026-56131, CVE-2026-56412, CVE-2026-66046, CVE-2026-76641, CVE-2026-76957                                                                                                                                                                                                                                                                                                                                                                                                 |
| ffmpeg          | CVE-2026-52295, CVE-2026-52296, CVE-2026-52297, CVE-2026-64830, CVE-2026-64831, CVE-2026-64832, CVE-2026-64833, CVE-2026-64834, CVE-2026-64835, CVE-2026-65703, CVE-2026-65704, CVE-2026-65705, CVE-2026-65706, CVE-2026-66036, CVE-2026-66037, CVE-2026-66038, CVE-2026-66039, CVE-2026-66040, CVE-2026-66041, CVE-2026-70628, CVE-2026-70629, CVE-2026-70630, CVE-2026-70631, CVE-2026-70632, CVE-2026-75141, CVE-2026-75142, CVE-2026-75143, CVE-2026-75144, CVE-2026-75145, CVE-2026-75146, CVE-2026-75147 |
| gdk-pixbuf      | CVE-2026-5201                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| ghostscript     | CVE-2026-39919                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| git             | CVE-2024-52005                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| glibc           | CVE-2026-8674, CVE-2026-18374, CVE-2026-19499, CVE-2026-19542, CVE-2026-77117, CVE-2026-80489, CVE-2026-89092                                                                                                                                                                                                                                                                                                                                                                                                  |
| graphene        | CVE-2026-81281                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| gstreamer1.0    | CVE-2026-73433, CVE-2026-73434                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| libevent        | CVE-2026-63379, CVE-2026-63381, CVE-2026-63382, CVE-2026-63383, CVE-2026-63384, CVE-2026-63385, CVE-2026-63387, CVE-2026-63388, CVE-2026-63495                                                                                                                                                                                                                                                                                                                                                                 |
| libgcrypt       | CVE-2024-2236                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| libgit2         | CVE-2026-5917, CVE-2026-53583, CVE-2026-53584, CVE-2026-53585, CVE-2026-53586, CVE-2026-53587                                                                                                                                                                                                                                                                                                                                                                                                                  |
| libpcap         | CVE-2026-0799, CVE-2026-6244, CVE-2026-6554, CVE-2026-18238, CVE-2026-18313, CVE-2026-31911, CVE-2026-31912                                                                                                                                                                                                                                                                                                                                                                                                    |
| libpcre2        | CVE-2026-86145, CVE-2026-89156, CVE-2026-89157, CVE-2026-89158, CVE-2026-89160, CVE-2026-89161, CVE-2026-89162                                                                                                                                                                                                                                                                                                                                                                                                 |
| libslirp        | CVE-2026-9539                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| libsndfile1     | CVE-2024-50613, CVE-2025-52194                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| libsolv         | CVE-2026-48863                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

continues on next page

Tabella 1 – continua dalla pagina precedente

| Recipe    | CVE IDs                                                                                                                                    |
|-----------|--------------------------------------------------------------------------------------------------------------------------------------------|
| libsoup   | CVE-2026-3099, CVE-2026-3632, CVE-2026-3633, CVE-2026-3634, CVE-2026-12548, CVE-2026-12549, CVE-2026-66337, CVE-2026-66338, CVE-2026-66339 |
| libtheora | CVE-2026-5673                                                                                                                              |
| libxfont  | CVE-2026-44950                                                                                                                             |
| libxfont2 | CVE-2026-44950, CVE-2026-59679                                                                                                             |
| libxml2   | CVE-2026-86137, CVE-2026-86138, CVE-2026-86139, CVE-2026-86140, CVE-2026-86141, CVE-2026-86142, CVE-2026-86143, CVE-2026-86144             |

continues on next page

Tabella 1 – continua dalla pagina precedente

| Recipe      | CVE IDs                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| linux-yocto | CVE-2019-14899, CVE-2021-3714, CVE-2021-3864, CVE-2022-0400,<br>CVE-2022-1247, CVE-2022-4543, CVE-2023-3397, CVE-2023-3640,<br>CVE-2023-6238, CVE-2023-6240, CVE-2025-71074, CVE-2025-71306,<br>CVE-2025-71308, CVE-2025-71313, CVE-2026-23328, CVE-2026-23374,<br>CVE-2026-23377, CVE-2026-23459, CVE-2026-31501, CVE-2026-31771,<br>CVE-2026-31777, CVE-2026-43009, CVE-2026-43022, CVE-2026-43042,<br>CVE-2026-43045, CVE-2026-43053, CVE-2026-43095, CVE-2026-43115,<br>CVE-2026-43131, CVE-2026-43174, CVE-2026-43191, CVE-2026-43204,<br>CVE-2026-43228, CVE-2026-43299, CVE-2026-43308, CVE-2026-43310,<br>CVE-2026-43311, CVE-2026-43326, CVE-2026-43344, CVE-2026-43391,<br>CVE-2026-43414, CVE-2026-43443, CVE-2026-45961, CVE-2026-45963,<br>CVE-2026-45991, CVE-2026-46008, CVE-2026-46017, CVE-2026-46032,<br>CVE-2026-46153, CVE-2026-46210, CVE-2026-46245, CVE-2026-46298,<br>CVE-2026-46302, CVE-2026-46311, CVE-2026-46330, CVE-2026-52949,<br>CVE-2026-52956, CVE-2026-52960, CVE-2026-52965, CVE-2026-52988,<br>CVE-2026-53007, CVE-2026-53008, CVE-2026-53009, CVE-2026-53017,<br>CVE-2026-53024, CVE-2026-53025, CVE-2026-53089, CVE-2026-53091,<br>CVE-2026-53102, CVE-2026-53106, CVE-2026-53108, CVE-2026-53113,<br>CVE-2026-53124, CVE-2026-53178, CVE-2026-53222, CVE-2026-53257,<br>CVE-2026-53285, CVE-2026-53292, CVE-2026-53308, CVE-2026-53313,<br>CVE-2026-53401, CVE-2026-63811, CVE-2026-63839, CVE-2026-63879,<br>CVE-2026-63941, CVE-2026-63977, CVE-2026-63983, CVE-2026-64013,<br>CVE-2026-64019, CVE-2026-64020, CVE-2026-64040, CVE-2026-64057,<br>CVE-2026-64067, CVE-2026-64068, CVE-2026-64070, CVE-2026-64079,<br>CVE-2026-64082, CVE-2026-64117, CVE-2026-64123, CVE-2026-64146,<br>CVE-2026-64154, CVE-2026-64159, CVE-2026-64160, CVE-2026-64210,<br>CVE-2026-64283, CVE-2026-64325, CVE-2026-64341, CVE-2026-64388,<br>CVE-2026-64400, CVE-2026-68086, CVE-2026-68103, CVE-2026-68105,<br>CVE-2026-68242, CVE-2026-68286, CVE-2026-68287, CVE-2026-68288,<br>CVE-2026-68289, CVE-2026-68291, CVE-2026-68295, CVE-2026-68303,<br>CVE-2026-68305, CVE-2026-68312, CVE-2026-68323, CVE-2026-68337,<br>CVE-2026-68375, CVE-2026-68399, CVE-2026-68404, CVE-2026-68436,<br>CVE-2026-68441, CVE-2026-68447, CVE-2026-68470, CVE-2026-72031,<br>CVE-2026-72064, CVE-2026-72091, CVE-2026-72315, CVE-2026-72329,<br>CVE-2026-72331, CVE-2026-72334, CVE-2026-72337, CVE-2026-72345,<br>CVE-2026-72355, CVE-2026-72370, CVE-2026-72377, CVE-2026-72380,<br>CVE-2026-72388, CVE-2026-72397, CVE-2026-72402, CVE-2026-72404,<br>CVE-2026-72413, CVE-2026-72423, CVE-2026-72440, CVE-2026-72454,<br>CVE-2026-72463, CVE-2026-72477, CVE-2026-72485, CVE-2026-72494,<br>CVE-2026-72496, CVE-2026-72497, CVE-2026-72499, CVE-2026-74258,<br>CVE-2026-74260, CVE-2026-74272, CVE-2026-74273, CVE-2026-74277,<br>CVE-2026-74289, CVE-2026-74291, CVE-2026-74294, CVE-2026-74307,<br>CVE-2026-74317, CVE-2026-74334, CVE-2026-74336, CVE-2026-74338,<br>CVE-2026-74342, CVE-2026-74347, CVE-2026-74350, CVE-2026-74354,<br>CVE-2026-74367, CVE-2026-74373, CVE-2026-74374, CVE-2026-74375,<br>CVE-2026-74407, CVE-2026-74419, CVE-2026-74449, CVE-2026-74466,<br>CVE-2026-74496, CVE-2026-74521, CVE-2026-74527, CVE-2026-74542, |

Tabella 1 – continua dalla pagina precedente

| Recipe               | CVE IDs                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| openssh              | CVE-2026-73281, CVE-2026-73282, CVE-2026-73283                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| perl                 | CVE-2026-15534                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| popt                 | CVE-2026-18739, CVE-2026-18743, CVE-2026-18839                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| python3              | CVE-2025-15367, CVE-2026-15310, CVE-2026-15806, CVE-2026-17084, CVE-2026-19672, CVE-2026-87910                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| python3-cryptography | CVE-2026-69247, CVE-2026-69248, CVE-2026-69249                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| python3-git          | CVE-2026-67322, CVE-2026-67323, CVE-2026-67324, CVE-2026-67325, CVE-2026-67326, CVE-2026-69097, CVE-2026-73619, CVE-2026-73620, CVE-2026-73621, CVE-2026-73622, CVE-2026-73623, CVE-2026-73624, CVE-2026-73625, CVE-2026-76217, CVE-2026-76218, CVE-2026-76219, CVE-2026-76220, CVE-2026-76221, CVE-2026-76222, CVE-2026-78675, CVE-2026-78676, CVE-2026-78677, CVE-2026-78678, CVE-2026-78679, CVE-2026-87817, CVE-2026-87818, CVE-2026-87819                                                                                                                                                                                                 |
| python3-lxml         | CVE-2026-49825                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| python3-pip          | CVE-2018-20225                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| python3-ply          | CVE-2025-56005                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| python3-urllib3      | CVE-2026-44432                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| qemu                 | CVE-2026-3195, CVE-2026-3196, CVE-2026-3842, CVE-2026-48914                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| qemu-system-native   | CVE-2026-3195, CVE-2026-3196, CVE-2026-3842, CVE-2026-48914                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| rpm-sequoia          | CVE-2026-2625                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| rsync                | CVE-2026-29518, CVE-2026-41035, CVE-2026-43617, CVE-2026-43618, CVE-2026-43619, CVE-2026-43620, CVE-2026-45232, CVE-2026-53783, CVE-2026-53784, CVE-2026-53785, CVE-2026-53786, CVE-2026-53788, CVE-2026-53789, CVE-2026-53790, CVE-2026-53791, CVE-2026-53792, CVE-2026-53793, CVE-2026-53794, CVE-2026-53795, CVE-2026-53796, CVE-2026-53797, CVE-2026-53798, CVE-2026-53799, CVE-2026-53800, CVE-2026-53801, CVE-2026-53802, CVE-2026-53803, CVE-2026-70452, CVE-2026-70453, CVE-2026-70454, CVE-2026-70456, CVE-2026-70457, CVE-2026-70458, CVE-2026-70459, CVE-2026-70460, CVE-2026-70461, CVE-2026-70462, CVE-2026-70463, CVE-2026-70464 |
| sudo                 | CVE-2026-82474                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| tar                  | CVE-2026-18477, CVE-2026-18508                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| util-linux           | CVE-2026-76642                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| util-linux-libuuid   | CVE-2026-76642                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| vim                  | CVE-2024-43802, CVE-2026-51400, CVE-2026-51401, CVE-2026-73070, CVE-2026-73071, CVE-2026-73075                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| webkitgtk            | CVE-2026-78376, CVE-2026-83596                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| xserver-xorg         | CVE-2026-55999, CVE-2026-56000                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| zlib                 | CVE-2026-85091                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

## Recipe Upgrades in 6.1

The following recipes have been upgraded:

| Recipe               | Previous version(s)  | New version(s)       |
|----------------------|----------------------|----------------------|
| acl                  | 2.3.2                | 2.4.0                |
| acpica               | 20251212             | 20260408             |
| adwaita-icon-theme   | 49.0                 | 50.0                 |
| alsa-lib             | 1.2.15.3             | 1.2.16.1             |
| alsa-ucm-conf        | 1.2.15.3             | 1.2.16.1             |
| alsa-utils           | 1.2.15.2             | 1.2.16               |
| appstream            | 1.1.2                | 1.2.0                |
| apr-util             | 1.6.3                | 1.6.5                |
| at-spi2-core         | 2.60.0               | 2.60.6               |
| attr                 | 2.5.2                | 2.6.0                |
| avahi                | 0.8                  | 0.9~rc5              |
| barebox              | 2026.04.0            | 2026.08.0            |
| barebox-tools        | 2026.04.0            | 2026.08.0            |
| bash-completion      | 2.17.0               | 2.18.0               |
| bind                 | 9.20.26              | 9.20.27              |
| binutils             | 2.46.1               | 2.47                 |
| binutils-cross       | 2.46.1               | 2.47                 |
| binutils-cross-canac | 2.46.1               | 2.47                 |
| binutils-crosssdk    | 2.46.1               | 2.47                 |
| binutils-testsuite   | 2.46.1               | 2.47                 |
| bluez5               | 5.86                 | 5.87                 |
| boost                | 1.90.0               | 1.92.0               |
| boost-build-native   | 1.90.0               | 1.92.0               |
| btrfs-tools          | 6.19.1               | 7.1                  |
| busybox              | 1.37.0               | 1.38.0               |
| busybox-inittab      | 1.37.0               | 1.38.0               |
| ca-certificates      | 20260601             | 20260816             |
| cargo                | 1.94.1               | 1.98.1               |
| cargo-c              | 0.10.21+cargo-0.95.0 | 0.10.25+cargo-0.99.0 |
| ccache               | 4.13.3               | 4.14                 |
| clang                | 22.1.8               | 23.1.0               |
| cmake                | 4.3.1                | 4.4.3                |
| cmake-native         | 4.3.1                | 4.4.3                |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe                     | Previous version(s) | New version(s) |
|----------------------------|---------------------|----------------|
| compiler-rt                | 22.1.8              | 23.1.0         |
| compi-<br>ler-rt-sanitizer | 22.1.8              | 23.1.0         |
| coreutils                  | 9.10                | 9.11           |
| createrepo-c               | 1.2.3               | 1.2.4          |
| cross-localedef-           | 2.43+git            | 2.44+git       |
| crypto-<br>dev-linux       | 1.14                | 1.14+git       |
| crypto-<br>dev-module      | 1.14                | 1.14+git       |
| crypto-<br>dev-tests       | 1.14                | 1.14+git       |
| cups                       | 2.4.16              | 2.4.19         |
| curl                       | 8.19.0              | 8.22.0         |
| debianutils                | 5.23.2              | 5.24           |
| debugedit                  | 5.2                 | 5.3            |
| dhcpcd                     | 10.3.1              | 10.5.2         |
| diffoscope                 | 314                 | 329            |
| diffstat                   | 1.68                | 1.69           |
| dos2unix                   | 7.5.4               | 7.5.7          |
| dropbear                   | 2025.89             | 2026.94        |
| dtc                        | 1.7.2               | 1.8.1          |
| ed                         | 1.22.5              | 1.22.6         |
| elfutils                   | 0.194               | 0.196          |
| enchant2                   | 2.8.15              | 2.8.21         |
| epiphany                   | 49.7                | 50.6           |
| erofs-utils                | 1.9.1               | 1.9.4          |
| ethtool                    | 6.19                | 7.1            |
| expat                      | 2.7.5               | 2.8.4          |
| fastfloat                  | 8.2.4               | 8.2.10         |
| ffmpeg                     | 8.0.3               | 8.1.2          |
| file                       | 5.47                | 5.48           |
| findutils                  | 4.10.0              | 4.11.0         |
| fmt                        | 12.1.0              | 12.2.0         |
| font-util                  | 1.4.1               | 1.4.2          |
| fontconfig                 | 2.17.1              | 2.18.3         |
| gawk                       | 5.4.0               | 5.4.1          |
| gcc                        | 15.3.0              | 16.2.0         |
| gcc-cross                  | 15.3.0              | 16.2.0         |
| gcc-cross-canadi           | 15.3.0              | 16.2.0         |
| gcc-crosssdk               | 15.3.0              | 16.2.0         |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe                          | Previous version(s)     | New version(s)          |
|---------------------------------|-------------------------|-------------------------|
| gcc-runtime                     | 15.3.0                  | 16.2.0                  |
| gcc-sanitizers                  | 15.3.0                  | 16.2.0                  |
| gcc-source                      | 15.3.0                  | 16.2.0                  |
| gdk-pixbuf                      | 2.44.5                  | 2.44.8                  |
| ghostscript                     | 10.06.0                 | 10.07.1                 |
| git                             | 2.53.0                  | 2.55.0                  |
| glib-2.0                        | 2.88.2                  | 2.88.3                  |
| glib-2.<br>0-initial            | 2.88.2                  | 2.88.3                  |
| glibc                           | 2.43+git                | 2.44+git                |
| glibc-locale                    | 2.43+git                | 2.44+git                |
| glibc-mtrace                    | 2.43+git                | 2.44+git                |
| glibc-scripts                   | 2.43+git                | 2.44+git                |
| glibc-testsuite                 | 2.43+git                | 2.44+git                |
| glslang                         | 1.4.341.0               | 1.4.357.0               |
| gn                              | 0+git (9d19a7870add...) | 0+git (17b0057970fa...) |
| gnu-config                      | 20250709+git            | 20260629+git            |
| gnupg                           | 2.5.17                  | 2.5.22                  |
| gnutls                          | 3.8.12                  | 3.8.13                  |
| go                              | 1.26.5                  | 1.27.1                  |
| go-binary-native                | 1.26.5                  | 1.27.1                  |
| go-cross-canadian               | 1.26.5                  | 1.27.1                  |
| go-cross-core2-3                | 1.26.5                  | 1.27.1                  |
| go-crosssdk                     | 1.26.5                  | 1.27.1                  |
| go-runtime                      | 1.26.5                  | 1.27.1                  |
| gpgme                           | 2.0.1                   | 2.1.2                   |
| gst-devtools                    | 1.28.5                  | 1.28.6                  |
| gst-examples                    | 1.28.5                  | 1.28.6                  |
| gststreamer1.0                  | 1.28.5                  | 1.28.6                  |
| gststreamer1.<br>0-libav        | 1.28.5                  | 1.28.6                  |
| gststreamer1.<br>0-plugins-bad  | 1.28.5                  | 1.28.6                  |
| gststreamer1.<br>0-plugins-base | 1.28.5                  | 1.28.6                  |
| gststreamer1.<br>0-plugins-good | 1.28.5                  | 1.28.6                  |
| gststreamer1.<br>0-plugins-ugly | 1.28.5                  | 1.28.6                  |
| gststreamer1.<br>0-python       | 1.28.5                  | 1.28.6                  |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe                     | Previous version(s) | New version(s) |
|----------------------------|---------------------|----------------|
| gststreamer1.0-rtsp-server | 1.28.5              | 1.28.6         |
| gtk-doc                    | 1.35.1              | 1.36.1         |
| gtk4                       | 4.22.2              | 4.22.4         |
| harfbuzz                   | 12.3.2              | 14.4.0         |
| hwdata                     | 0.406               | 0.410          |
| igt-gpu-tools              | 2.3                 | 2.5            |
| inetutils                  | 2.7                 | 2.8            |
| iproute2                   | 6.19.0              | 7.2.0          |
| json-c                     | 0.18                | 0.19           |
| kbd                        | 2.9.0               | 2.10.0         |
| kea                        | 3.0.3               | 3.2.0          |
| less                       | 692                 | 704            |
| libadwaita                 | 1.8.4               | 1.9.3          |
| libarchive                 | 3.8.7               | 3.8.9          |
| libcap                     | 2.77                | 2.78           |
| libcap-ng                  | 0.9.1               | 0.9.5          |
| libcap-ng-python           | 0.9.1               | 0.9.5          |
| libcxx                     | 22.1.8              | 23.1.0         |
| libdi-splay-info           | 0.3.0               | 0.4.0          |
| libdrm                     | 2.4.131             | 2.4.134        |
| libedit                    | 20251016-3.1        | 20260512-3.1   |
| libevdev                   | 1.13.6              | 1.13.7         |
| libevent                   | 2.1.12              | 2.1.13         |
| libffi                     | 3.5.2               | 3.8.0          |
| libfyaml                   | 0.9.4               | 0.9.6          |
| libgcc                     | 15.3.0              | 16.2.0         |
| libgcc-initial             | 15.3.0              | 16.2.0         |
| libgcrypt                  | 1.12.1              | 1.12.3         |
| libgfortran                | 15.3.0              | 16.2.0         |
| libgit2                    | 1.9.2               | 1.9.7          |
| libgpg-error               | 1.59                | 1.61           |
| libical                    | 3.0.20              | 4.0.5          |
| libinput                   | 1.30.2              | 1.31.3         |
| libjpeg-turbo              | 3.1.3               | 3.2.0          |
| libksba                    | 1.6.8               | 1.8.1          |
| libmd                      | 1.1.0               | 1.2.0          |
| libmicrohttpd              | 1.0.2               | 1.0.10         |
| libmodulemd                | 2.15.2              | 2.15.3         |

continues on next page



Tabella 2 – continua dalla pagina precedente

| Recipe              | Previous version(s) | New version(s)         |
|---------------------|---------------------|------------------------|
| libmpc              | 1.3.1               | 1.4.1                  |
| libpcre2            | 10.47               | 10.48                  |
| libpng              | 1.6.56              | 1.6.58                 |
| libportal           | 0.9.1               | 0.10.0                 |
| libpsl              | 0.21.5              | 0.23.3                 |
| librepo             | 1.20.0              | 1.21.0                 |
| librsvg             | 2.61.3              | 2.62.3                 |
| libseccomp          | 2.6.0               | 2.6.1                  |
| libslirp            | 4.9.1               | 4.9.4                  |
| libsolv             | 0.7.36              | 0.7.39                 |
| libstd-rs           | 1.94.1              | 1.98.1                 |
| libtool             | 2.5.4               | 2.6.2                  |
| libtool-cross       | 2.5.4               | 2.6.2                  |
| libtool-native      | 2.5.4               | 2.6.2                  |
| libusb1             | 1.0.29              | 1.0.30                 |
| libva               | 2.23.0              | 2.24.1                 |
| libva-initial       | 2.23.0              | 2.24.1                 |
| libva-utils         | 2.23.0              | 2.24.0                 |
| libxfont2           | 2.0.7               | 2.0.9                  |
| libxi               | 1.8.2               | 1.8.3                  |
| libxkbcommon        | 1.13.1              | 1.13.2                 |
| libxmlb             | 0.3.25              | 0.3.29                 |
| lighttpd            | 1.4.82              | 1.4.85                 |
| linux-firmware      | 20260410            | 20260810               |
| li-nux-libc-headers | 6.18                | 7.2                    |
| linux-yocto         | 6.18.39+git         | 6.18.48+git, 7.2.2+git |
| li-nux-yocto-dev    | 7.0+git             | 7.2+git                |
| linux-yocto-rt      | 6.18.39+git         | 6.18.48+git, 7.2.2+git |
| li-nux-yocto-tiny   | 6.18.39+git         | 6.18.48+git, 7.2.2+git |
| lld                 | 22.1.8              | 23.1.0                 |
| lldb                | 22.1.8              | 23.1.0                 |
| llvm                | 22.1.8              | 23.1.0                 |
| ll-vm-tblgen-native | 22.1.8              | 23.1.0                 |
| log4cplus           | 2.1.2               | 2.2.0.1                |
| lsof                | 4.99.6              | 4.99.7                 |
| ltp                 | 20260130            | 20260529               |
| lttng-modules       | 2.14.4              | 2.16.0                 |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe                 | Previous version(s)        | New version(s)             |
|------------------------|----------------------------|----------------------------|
| lttng-tools            | 2.14.1                     | 2.16.0                     |
| lttng-ust              | 2.14.0                     | 2.16.0                     |
| lua                    | 5.5.0                      | 5.5.1                      |
| lzip                   | 1.25                       | 1.26                       |
| makedumpfile           | 1.7.8                      | 1.7.9                      |
| man-pages              | 6.17                       | 6.19                       |
| mesa                   | 26.0.5                     | 26.2.2                     |
| mesa-demos             | 9.0.0                      | 9.0.0+git                  |
| mesa-gl                | 26.0.5                     | 26.2.2                     |
| me-<br>sa-tools-native | 26.0.5                     | 26.2.2                     |
| meson                  | 1.10.2                     | 1.12.0                     |
| minicom                | 2.10                       | 2.11.1                     |
| mkfontscale            | 1.2.3                      | 1.2.4                      |
| mpg123                 | 1.33.4                     | 1.33.7                     |
| msmtp                  | 1.8.32                     | 1.8.34                     |
| nasm                   | 3.01                       | 3.02                       |
| native-<br>sdk-libtool | 2.5.4                      | 2.6.2                      |
| neard                  | 0.19                       | 0.20                       |
| netbase                | 6.5                        | 6.6                        |
| nettle                 | 3.10.2                     | 4.0                        |
| nfs-utils              | 2.8.7                      | 2.9.2                      |
| nghttp2                | 1.68.1                     | 1.70.0                     |
| openmp                 | 22.1.8                     | 23.1.0                     |
| opensbi                | 1.8.1                      | 1.9                        |
| openssh                | 10.3p1                     | 10.5p1                     |
| openssl                | 3.5.7                      | 4.0.2                      |
| opkg                   | 0.9.0                      | 0.10.0                     |
| orc                    | 0.4.42                     | 0.4.43                     |
| ovmf                   | edk2-stable202511          | edk2-stable202605          |
| p11-kit                | 0.26.4                     | 0.26.5                     |
| pango                  | 1.57.0                     | 1.58.2                     |
| parted                 | 3.6                        | 3.7                        |
| patchelf               | 0.18.0+git                 | 0.19.1                     |
| pciutils               | 3.14.0                     | 3.15.0                     |
| perl                   | 5.42.0                     | 5.44.0                     |
| piglit                 | 1.0+gitr (a0a27e528f64...) | 1.0+gitr (56f237be32ed...) |
| pinentry               | 1.3.2                      | 1.3.3                      |
| pkgconf                | 2.5.1                      | 3.0.6                      |
| powertop               | 2.15                       | 2.16                       |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe              | Previous version(s)       | New version(s)            |
|---------------------|---------------------------|---------------------------|
| ppp                 | 2.5.2                     | 2.5.3                     |
| procps              | 4.0.6                     | 4.0.7                     |
| puzzles             | 0.0+git (ecb576fb2a0a...) | 0.0+git (3c3632259d29...) |
| python3             | 3.14.6                    | 3.14.7                    |
| python3-attrs       | 25.4.0                    | 26.1.0                    |
| python3-build       | 1.4.0                     | 1.6.0                     |
| py-thon3-certifi    | 2026.2.25                 | 2026.7.22                 |
| python3-cffi        | 2.0.0                     | 2.1.1                     |
| python3-click       | 8.3.1                     | 8.5.0                     |
| py-thon3-cryptograf | 46.0.7                    | 50.0.1                    |
| py-thon3-cryptograf | 46.0.7                    | 50.0.1                    |
| python3-cython      | 3.2.4                     | 3.2.9                     |
| py-thon3-docutils   | 0.22.4                    | 0.23                      |
| python3-dtc         | 1.7.2                     | 1.8.1                     |
| py-thon3-dtschema   | 2025.12                   | 2026.6                    |
| py-thon3-editables  | 0.5                       | 0.6                       |
| python3-git         | 3.1.43                    | 3.1.61                    |
| py-thon3-hatchling  | 1.29.0                    | 1.31.0                    |
| py-thon3-hypothesis | 6.151.9                   | 6.167.0                   |
| python3-idna        | 3.11                      | 3.19                      |
| py-thon3-imagesize  | 2.0.0                     | 2.0.1                     |
| py-thon3-installer  | 0.7.0                     | 1.0.1                     |
| py-thon3-jsonpointe | 3.0.0                     | 3.1.1                     |
| python3-lxml        | 6.0.2                     | 6.1.2                     |
| python3-mako        | 1.3.10                    | 1.4.1                     |
| py-thon3-markdown   | 3.10.2                    | 3.10.3                    |
| py-thon3-maturin    | 1.12.4                    | 1.15.0                    |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe              | Previous version(s) | New version(s) |
|---------------------|---------------------|----------------|
| py-thon3-meson-pytl | 0.19.0              | 0.20.0         |
| python3-numpy       | 2.4.3               | 2.5.2          |
| py-thon3-packaging  | 26.0                | 26.3           |
| py-thon3-pathspect  | 1.0.4               | 1.1.1          |
| python3-pbr         | 7.0.3               | 7.1.0          |
| python3-pdm         | 2.26.6              | 2.29.0         |
| py-thon3-pdm-backer | 2.4.7               | 2.4.9          |
| python3-pip         | 26.0.1              | 26.2.1         |
| py-thon3-poetry-cor | 2.3.1               | 2.4.1          |
| py-thon3-pycairo    | 1.29.0              | 1.29.1         |
| py-thon3-pyelftools | 0.32                | 0.33           |
| py-thon3-pygments   | 2.19.2              | 2.21.0         |
| py-thon3-pygobject  | 3.56.1              | 3.58.0         |
| py-thon3-pyopenssl  | 26.0.0              | 26.4.0         |
| py-thon3-pyproject- | 0.11.0              | 0.12.1         |
| python3-pytest      | 9.0.2               | 9.1.1          |
| python3-pytz        | 2026.1              | 2026.3         |
| py-thon3-requests   | 2.32.5              | 2.34.2         |
| py-thon3-rpds-py    | 0.30.0              | 2026.6.3       |
| py-thon3-sbom-cve-c | 1.3.1               | 1.3.3          |
| python3-scons       | 4.10.1              | 4.11.1         |
| py-thon3-setuptools | 82.0.1              | 84.0.0         |
| py-thon3-setuptools | 1.12.0              | 1.13.0         |
| py-thon3-setuptools | 9.2.2               | 10.2.3         |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe              | Previous version(s)   | New version(s)        |
|---------------------|-----------------------|-----------------------|
| py-thon3-shacl2code | 1.0.1                 | 1.1.0                 |
| py-thon3-snowballst | 3.0.1                 | 3.1.1                 |
| py-thon3-spdx-pythc | 0.0.5                 | 0.0.6                 |
| py-thon3-sphinx-arc | 0.5.2                 | 0.6.1                 |
| py-thon3-testtools  | 2.8.7                 | 2.9.1                 |
| py-thon3-trove-clas | 2026.1.14.14          | 2026.6.1.19           |
| py-thon3-typing-ext | 4.15.0                | 4.16.0                |
| py-thon3-uritools   | 6.0.1                 | 6.1.3                 |
| py-thon3-urllib3    | 2.6.3                 | 2.7.0                 |
| py-thon3-uv-build   | 0.10.10               | 0.12.9                |
| py-thon3-wcwidth    | 0.6.0                 | 0.8.3                 |
| py-thon3-websockets | 16.0                  | 17.1                  |
| python3-wheel       | 0.46.3                | 0.48.0                |
| python3-zipp        | 3.23.0                | 4.1.0                 |
| qemu                | 10.2.0                | 11.1.1                |
| qemu-native         | 10.2.0                | 11.1.1                |
| qe-mu-system-native | 10.2.0                | 11.1.1                |
| re2c                | 4.4                   | 4.6                   |
| repo                | 2.61.1                | 2.66.1                |
| resolvconf          | 1.94                  | 1.95                  |
| rpm                 | 4.20.1                | 6.0.2                 |
| rpm-sequoia         | 1.10.1                | 1.10.2                |
| rpm-sequoia-cryp    | git (f3f5fa454345...) | git (359ab169da6a...) |
| rsync               | 3.4.1                 | 3.5.0                 |
| ruby                | 4.0.5                 | 4.0.6                 |
| rust                | 1.94.1                | 1.98.1                |
| ru-st-cross-canadi  | 1.94.1                | 1.98.1                |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe              | Previous version(s) | New version(s)    |
|---------------------|---------------------|-------------------|
| sbom-cve-check-ut   | 2026-05-07          | 2026-08-25        |
| sbom-cve-check-ut   | 2026.05.07-000006   | 2026.08.25-000009 |
| scdoc               | 1.11.4              | 1.11.5            |
| screen              | 5.0.1               | 5.0.2             |
| shaderc             | 2026.1              | 2026.3            |
| shadow              | 4.19.4              | 4.20.2            |
| shared-mime-info    | 2.4                 | 2.5.1             |
| spirv-headers       | 1.4.341.0           | 1.4.357.0         |
| spirv-llvm-trans    | 22.1.1              | 23.1.1            |
| spirv-tools         | 1.4.341.0           | 1.4.357.0         |
| sqlite3             | 3.51.3              | 3.53.4            |
| strace              | 6.19                | 7.2               |
| stress-ng           | 0.20.01             | 0.22.00           |
| swig                | 4.4.1               | 4.5.0             |
| sysstat             | 12.7.9              | 12.8.0            |
| systemd             | 259.5               | 261.2             |
| systemd-boot        | 259.5               | 261.2             |
| systemd-boot-native | 259.5               | 261.2             |
| systemtap           | 5.4                 | 5.5               |
| systemtap-native    | 5.4                 | 5.5               |
| taglib              | 2.2.1               | 2.3.1             |
| tc-agent            | 1.9.0               | 1.11.0            |
| tcl                 | 9.0.3               | 9.0.4             |
| tcl8                | 8.6.17              | 8.6.18            |
| tiff                | 4.7.1               | 4.7.2             |
| time                | 1.9                 | 1.10              |
| ttyrun              | 2.41.0              | 2.44.0            |
| u-boot              | 2026.01             | 2026.07           |
| u-boot-tools        | 2026.01             | 2026.07           |
| utfcpp              | 4.0.9               | 4.2.0             |
| util-linux          | 2.41.5              | 2.42.3            |
| util-linux-libuu    | 2.41.5              | 2.42.3            |
| vala                | 0.56.18             | 0.56.19           |
| valgrind            | 3.26.0              | 3.27.1            |
| vim                 | 9.2.0340            | 9.2.0993          |
| vim-tiny            | 9.2.0340            | 9.2.0993          |
| virglrenderer       | 1.2.0               | 1.3.0             |
| vte                 | 0.82.2              | 0.84.1            |
| vulkan-headers      | 1.4.341.0           | 1.4.357.0         |

continues on next page

Tabella 2 – continua dalla pagina precedente

| Recipe           | Previous version(s)   | New version(s)        |
|------------------|-----------------------|-----------------------|
| vulkan-loader    | 1.4.341.0             | 1.4.357.0             |
| vulkan-samples   | git (fa2cf45adde0...) | git (383471195757...) |
| vulkan-tools     | 1.4.341.0             | 1.4.357.0             |
| vul-             | 1.4.341.0             | 1.4.357.0             |
| kan-utility-libr |                       |                       |
| vul-             | 1.4.341.0             | 1.4.357.0             |
| kan-validation-l |                       |                       |
| vulkan-volk      | 1.4.341.0             | 1.4.357.0             |
| waffle           | 1.8.1                 | 1.8.3                 |
| wayland          | 1.24.0                | 1.26.0                |
| way-             | 1.47                  | 1.49                  |
| land-protocols   |                       |                       |
| webkitgtk        | 2.50.6                | 2.52.6                |
| weston           | 15.0.0                | 16.0.0                |
| which            | 2.23                  | 2.25                  |
| wireless-regdb   | 2026.05.30            | 2026.09.03            |
| wpa-supPLICant   | 2.11                  | 2.12                  |
| xev              | 1.2.6                 | 1.2.7                 |
| xkey-            | 2.47                  | 2.48                  |
| board-config     |                       |                       |
| xmodmap          | 1.0.11                | 1.0.12                |
| xrandr           | 1.5.3                 | 1.5.4                 |
| xset             | 1.2.5                 | 1.2.6                 |
| xvinfo           | 1.1.5                 | 1.1.6                 |
| xwininfo         | 1.1.6                 | 1.1.7                 |
| xz               | 5.8.2                 | 5.8.3                 |

## Contributors to 6.1

Thanks to the following people who contributed to this release:

- Adam Blank
- Adam Duskett
- Adarsh Jagadish Kamini
- Aditya GS
- Adrian Freihofer
- Alejandro Hernandez Samaniego
- Alejandro Mery
- Alessandro Zini
- Alexander Kanavin

- Alexander Stein
- Alex Kiernan
- Amaury Couderc
- Anders Heimer
- Andreas Mützel
- Andrei Lalaev
- Andrej Valek
- Andrew Geissler
- Anis Bougrine
- Ankur Tyagi
- Anthony Squires
- Antoine Gouby
- Antonin Godard
- Anton Skorup
- Aravind Bandari
- AshishKumar Mishra
- Aswin Murugan
- Aurelien DESBRIERES
- Baban
- Babanpreet Singh
- Benjamin Robin
- Bin Cao
- Bruce Ashfield
- Changqing Li
- Chen Qi
- Chris Laplante
- Colin Pinnell McAllister
- Corentin Guillevic
- Daiane Angolini
- Daniel Dragomir
- Daniel McGregor
- Daniel Turull



- David Nyström
- David Reyna
- Dawid Bijak
- Deepesh Varatharajan
- Denys Dmytriienko
- Devansh Patel
- Dmitry Baryshkov
- Dmitry Sakhonchik
- Efe Can Icoz
- Eilís 'pidge' Ní Fhlannagáin
- El Mehdi YOUNES
- Enoch Ng
- Enzo Frese
- Eric Meyers
- Ernest Van Hoecke
- Esa Jaaskela
- Etienne Cordonnier
- Fabian Pflug
- Fabien Lehoussel
- Fabio Estevam
- Florin Diaconescu
- Francesco Valla
- Francisco Pedraza
- Fredrik Svensson (svsvenss)
- Frieder Schrempf
- Gabriel Smith
- Gavvala, Kris
- George Refseth
- Ghanshyam Banait
- Guðni Már Gilbert
- Gustavo Henrique Nihei
- Haiqing Bai

- Haixiao Yan
- Hangtian Zhu
- Harald Brinkmann
- Harish Sadineni
- Hemanth Kumar M D
- Hetvi Thakar
- Hiago De Franco
- Himani Barde
- Himani Ramesh Barde
- Himanshu Jadon
- hongxu
- Igor Opaniuk
- Ivan Nestlerode
- jackyu.lee
- Jaeyoon Jung
- Jaipaul Cheernam
- Jamin Lin
- Jan Vermaete
- Jate Sujjavanich
- Jesse Van Gavere
- Jinfeng Wang
- Jinwang Li
- Joao Marcos Costa
- João Marcos Costa
- Johan Anderholm
- John Ripple
- Jonas Juffinger
- Jörg Sommer
- Jose Quaresma
- Joshua Watt
- Juhandré Knoetze
- Junjie Cao

- Kanksha Paturi
- Karthik
- KAZUYOSHI AKIYAMA (秋山和慶)
- Khem Raj
- Kris Gavvala
- Kyungjik Min
- Lee Chee Yang
- Leon Anavi
- Leonardo Costa
- Leonid Iziumtsev
- Levi Shafter
- Lian Wang
- Li Wang
- Li Zhou
- Luca Fancellu
- Marcio Henriques
- Marcus Flyckt
- Marek Vasut
- Mark Hatle
- Mark Jonas
- Markus Swarowsky
- Markus Volk
- mark.yang
- Marta Rybczynska
- Martin Jansa
- Mathieu Dubois-Briand
- Matt Madison
- Mengshi Wu
- Michael Halstead
- Michael Opdenacker
- Michael Tretter
- Michal Sieron

- Mikko Rapeli
- Mingli Yu
- Minwoo Choi
- Moritz Haase
- Nate Kent
- Nathaniel White
- Nick Owens
- Nico
- Nicolas Dechesne
- Niko Mauno
- Nora Schiffer
- Oleksiy Obitotskyy
- Omkar Patil
- Otavio Salvador
- Pascal Eberhard
- Paul Barker
- Paul Eggleton
- Peter Kjellerstedt
- Peter Marko
- Peter Tatrai
- Philip Lorenz
- Prabhudasu Vatala
- Pratik Farkase
- Quan Sun
- Quentin Schulz
- Rasmus Villemoes
- Ricardo Salveti
- Richard Purdie
- Robert P. J. Day
- Robert Yang
- Rob Woolley
- Roland Kovacs

- Ross Burton
- Rouven Czerwinski
- Rouven Rastetter
- Ryan Eatmon
- Sai Sneha
- Sam Kent
- Sandeep J
- Sebastian Muxel
- Sergio Prado
- sh0127.shin
- Shinu Chandran
- Siddharth Doshi
- Siva Balasubramanian
- Sudhir Dumbhare
- Sumanth Gavini
- Sundeep KOKKONDA
- Sunil Dora
- Tafil Avdyli
- Tan Siewert
- Taruntej Kanakamalla
- Tejas Kanfode
- Theo Gaige (Schneider Electric)
- Thomas Perrot
- Thorsten Schmelzer
- Thune Tran
- Tim Orling
- Trevor Gamblin
- Trevor Woerner
- T, Sai Sireesha
- Tushar Darote
- Ulrich Ölmann
- Vijay Anusuri

- Viswanath Kraleti
- Vivek Puar
- Vyacheslav Yurkov
- Walter Werner Schneider
- Wang Mingyu
- Wei Deng
- Wei Gao
- Wei Zhang
- Wenwen Fu
- Wes Malone
- WXbet
- Xiaozhan Li
- Xiuzhuo Shang
- Yann Dirson
- Yash Shinde
- Yoann Congal
- Yogesh Tyagi
- Zheng Ruoqin
- Zhixiong Chi
- Zk47T
- Zoltán Böszörményi

## Repositories / Downloads for Yocto-6.1

### 17.2.2 Migration notes for 6.1 (blacksail)

This section provides migration information for moving to the Yocto Project 6.1 Release (codename "blacksail") from the prior release. For a list of new features and enhancements, see the [Release notes for 6.1 \(blacksail\)](#) section.

#### Supported kernel versions

The `OLDEST_KERNEL` setting is 5.15 in this release, meaning that out the box, older kernels are not supported. See [4.3 migration notes](#) for details.

## Supported distributions

Compared to the previous releases, running BitBake is supported on new GNU/Linux distributions:

- AlmaLinux 10
- Fedora 44
- Rocky Linux 10

See *all supported distributions*.

## useradd: replace GROUPMEMS\_PARAM assignments to USERMOD\_PARAM

The `groupmems` command is removed from the `shadow` recipe starting from version 4.20. The same functionality provided by `groupmems` can be achieved with the `usermod` command.

Assignments made to the `GROUPMEMS_PARAM` variable can be converted to use `USERMOD_PARAM`, by replacing:

```
GROUPMEMS_PARAM:${PN} = "--add user --group group1; \  
                        --add user --group group2"
```

With:

```
USERMOD_PARAM:${PN} = "--append --groups group1 user; \  
                      --append --groups group2 user"
```

Or written more simply as:

```
USERMOD_PARAM:${PN} = "--append --groups group1,group2 user"
```

See (b8da733) for more details.

## Removal of oe.utils.all\_distro\_features() and oe.utils.any\_distro\_features()

The `oe.utils.all_distro_features()` and `oe.utils.any_distro_features()` functions have been removed from *OpenEmbedded-Core (OE-Core)*.

Those can be replaced by `bb.utils.contains()` and `bb.utils.contains_any()` calls:

```
oe.utils.all_distro_features("x y", ...) -> bb.utils.contains("DISTRO_FEATURES",  
↪ "x y", ...)
```

And:

```
oe.utils.any_distro_features("x y", ...) -> bb.utils.contains_any("DISTRO_FEATURES  
↪ ", "x y", ...)
```

### *LICENSE is now a SPDX License Expression*

The *LICENSE* variable is now a *SPDX License Expression* instead of the custom license expressions that have been used historically.

The changes required for the new expressions are as follows:

1. The `&` operator is replaced with `AND`
2. The `|` operator is replaced with `OR`
3. Any license value which is not a valid *SPDX License Expression* is an error.
4. Custom (non *SPDX License Identifier*) licenses are still allowed, as long as they are prefixed with `LicenseRef-`. The behavior of looking for the license text in *LICENSE\_PATH* (with or without the `LicenseRef-` prefix) or *NO\_GENERIC\_LICENSE* is unchanged, and may still be used.
5. `CLOSED` as a license is deprecated and will issue a warning. This license is effectively "no license" (usually meaning e.g. "All rights reserved"), but a more precise definition is to provide some sort of actual license text using a custom license. This provides a more consistent definition of the license text, since the meaning of "no license" may vary by jurisdiction. Keep in mind that you can still have a common license file in *LICENSE\_PATH* and refer to it with a `LicenseRef-` license. Note that when you do this, you will also need to provide a *LIC\_FILES\_CHKSUM* value to point to your license file.
6. The generic `PD` (Public Domain) license is no longer allowed (since it is not a valid *SPDX License Identifier*). Additionally, the meaning of "Public Domain" varies by jurisdiction, so leaving the exact license text unspecified is not recommended. Instead, either find a matching SPDX license (The *SPDX License Check* website can be useful here), or use a `LicenseRef-` with *NO\_GENERIC\_LICENSE* to specify the actual license text.
7. The `WITH` operator should now be used to describe an exception to a license, instead of a bespoke license identifier. For example, the old bespoke license `Apache-2.0-with-LLVM-exception` would become `Apache-2.0 WITH LLVM-exception`. For a list of the valid license exceptions, see *SPDX License Exception*.
8. Because of the change to use `WITH` instead of bespoke licenses, there is a change in how *INCOMPATIBLE\_LICENSE* works. Anything listed in this variable will match a single license (unchanged), but it will also match the left-hand (license) side of a `WITH` expression. To allow a license with a specific *SPDX License Exception*, the SPDX license exception must be listed in *INCOMPATIBLE\_LICENSE\_EXCEPTIONS*.

Practically speaking, the place where this comes up the most is when attempting to exclude GPLv3 code using *INCOMPATIBLE\_LICENSE*. Previously, this would have allowed any `GPLv3-with-exception` license, since they were bespoke licenses that did not match the `GPL-3.0* LGPL-3.0*` expansion. Now, however, the licenses will match because they are e.g. `GPL-3.0-or-later WITH exception`. As such, any exceptions to the GPLv3 that should be allowed must be listed in *INCOMPATIBLE\_LICENSE\_EXCEPTIONS*.

Currently, the older syntax for license expressions is still parsed and automatically converted to a *SPDX License Expression*, but a warning is issued when this occurs. This support will eventually be removed and the only valid values for these variables will be *SPDX License Expression*.



 **Suggerimento**

The `scripts/contrib/convert-spdx-licenses.py` script can help converting *LICENSE* expressions in *layers*.

**Class file functions moved to the `oe` library**

Many class file functions have been moved to `oe` library in *OpenEmbedded-Core (OE-Core)*:

- *kernel*:
  - The `get_kernel*()` functions are now `oe.kernel.get*()`
  - The default kernel build `make` commands now set `ARCH`
  - The `valid_arches` variable is no longer available to change `ARCH`
- *kernel-arch* no longer exports or sets `ARCH` and `UBOOT_ARCH`, `oe.kernel.map_kernel_arch(d)` and `oe.kernel.map_uboot_arch(d)` should be used instead
- *kernel*, *uboot-config*: `ARCH` and `UBOOT_ARCH` are not exported into the environment in most cases
- Various *utils* class Python functions are now `oe.utils.XXX()` (see [meta/lib/oe/utils.py](#))
- Most *sanity* class functions are now `oe.sanity.XXX()` (see [meta/lib/oe/sanity.py](#))
- `lsb_distro_identifier` is now always `oe.lsb.distro_identifier()`

**Removed recipes**

- `libdazzle`, `libhandy`: No longer a dependency of the `epiphany` recipe, moved to *meta-gnome* (in *meta-openembedded*) ([32d91b6](#))
- `libpcrc`: Obsolete project now replaced by `libpcrc2` ([057cccd](#))
- `libxfont`: Recipe is obsolete and successor `libxfont2` is available, nothing depends on it in *OpenEmbedded-Core (OE-Core)* anymore ([4666968](#))
- `gptfdisk`: Remove recipe as there are no dependencies on this recipe in *OpenEmbedded-Core (OE-Core)* anymore ([188d84b](#))
- `libc1c`: Remove recipe as it was replaced by `mesa-libc1c` ([5457c35](#))
- `makedepend`: Remove recipe as `mesa` no longer depends on `makedepend` ([7e696b1](#))
- `python-six`: Moved to *meta-python* ([372ee47](#))

**Removed variables**

- `SDK_TOOLCHAIN_LANGS`: Merged into *SDK\_FEATURES* ([933981a](#))

**Removed *PACKAGECONFIG* options****Removed classes**

- `linux-kernel-base.bbclass`: Was removed as its functionality was moved to *kernel-arch*. Users of this class should now inherit *kernel-arch* instead.

## Miscellaneous changes

- *archiver*: srpm support for *ARCHIVER\_MODE* was removed (69ce759)
- *systemd-systemctl-native*: Rename to *systemd-tools-native* (ff985de)

## 17.3 Release 6.0 (wrynose)

### 17.3.1 Release notes for 6.0 (wrynose)

This document lists new features and enhancements for the Yocto Project 6.0 Release (codename "wrynose"). For a list of breaking changes and migration guides, see the *Migration notes for 6.0 (wrynose)* section.

The 6.0 (wrynose) release is the new LTS release after 5.0 (scarthgap). If you are migrating from the 5.0 version, be sure to read the previous migration guides:

- *Release 5.1 (styhead)*
- *Release 5.2 (walnascar)*
- *Release 5.3 (whinlatter)*

See also the list of new features and enhancements of the previous releases:

- *Release notes for 5.1 (styhead)*
- *Release notes for 5.2 (walnascar)*
- *Release notes for 5.3 (whinlatter)*

### New Features / Enhancements in 6.0

- Linux kernel 6.18, gcc 15.2, glibc 2.43, LLVM 22.1.2, and over 300 other recipe upgrades
- Minimum Python version required on the host: 3.9.
- Kernel-related changes:
  - *kernel-fit-image*: Support arbitrary loadables (2535427)
  - *kernel-yocto*: Allow enabling Rust in the kernel by adding `rust` to the *KERNEL\_FEATURES* (for Linux kernel recipes inheriting this class) (6719ed4)
  - Disable *ccache* support when Linux kernel Rust support is enabled (d80d006)
- New core recipes:
  - *libconfig*: Import recipe from <https://git.openembedded.org/meta-openembedded/>, needed by one of the Mesa recipes (1a0196a)
  - *python3-sphinxcontrib-svg2pdfconverter*: Used for the generation of the Yocto Project documentation (f3f0019)
  - *python3-pyzstd*: Import from *meta-python*, needed by the *ukify* tool of *systemd* v258 (88a2713)
  - *python3-uv-build*: This recipe adds the *uv* Python build backend, required by *python3-cryptography* (0880cd2)

- `blueprint-compiler`: Add the recipe as it became a dependency of the `epiphany` recipe after its upgrade to 49.2 (4212392)
  - `python3-sbom-cve-check`: New recipe for building and using `sbom-cve-check`, a lightweight SBOM CVE analysis tool (0fdacec)
  - `python3-shacl2code`, `python3-hatch-build-scripts`, `python3-spdx-python-model`: Added as dependencies of `python3-sbom-cve-check` (4862221, 41591af, a83eaca)
  - `libfyaml`: Added as a dependency of `appstream` (b8b7b58)
  - `meta-world-recipe-sbom`: Building this recipe will produce SBOM documents for each recipe present in the build environment, using the `create-spdx` class. This is different from the image SBOM which can also be generated using the `create-spdx` class after building an image. See *Creating a Software Bill of Materials* for more information (d999ac4)
  - `python3-kirk`: The Kirk application is a fork of `runltp-ng` and became the official LTP tests executor (c33fd4e)
  - `wic`: This recipe builds the *WIC* command-line tool. This used to be part of *OpenEmbedded-Core (OE-Core)* but is now externally managed (25ca1cb, b9e2a2f)
- New core classes:
    - `kernel-yocto-rust`: Adds the required dependencies to build the Rust components of the Linux kernel (6c90097)
    - `module-rust`: Support for building out-of-tree Rust kernel modules. An example recipe using this class can be found in `meta-skeleton/recipes-kernel/rust-out-of-tree-module` (76fd22f, 76fd22f)
    - `sbom-cve-check`: Class for post-build CVE analysis of an image, which uses the `sbom-cve-check` tool internally (8ef22ad)
    - `sbom-cve-check-recipe`: Class for post-build CVE analysis of recipes (using the recipe SBOM, meaning building the software provided by the recipe is not needed), which uses the `sbom-cve-check` tool internally. This also obsoletes the `cve-check` class. (e2518b1, 00de455)
  - New variables:
    - The `OPENSSH_HOST_KEY_DIR` variable can be used to specify the directory where OpenSSH host keys are stored. The default value is `/etc/ssh` (add80d)
    - The `OPENSSH_HOST_KEY_DIR_READONLY_CONFIG` variable can be used to specify the directory where OpenSSH host keys are stored when the device uses a read-only filesystem. The default value is `/var/run/ssh` (add80d)
    - The `SPDX_INCLUDE_KERNEL_CONFIG` can be set to "1" to export the Linux kernel configuration (`CONFIG_*` parameters) into the SPDX document when using the `create-spdx` class (228a968)
    - The `SPDX_INCLUDE_PACKAGECONFIG` variable can be set to "1" to export a recipe's `PACKAGECONFIG` features (enabled/disabled) into the SPDX document when using the `create-spdx` class (228a968)
    - The `SPDX_PACKAGE_URL` allows specifying a space-separated list of Package URLs (purls) for the software Package when using the `create-spdx` class (874b2d3)

- The `SPDX_GIT_PURL_MAPPINGS` variable allows mapping domain names to PURLs (Package URLs) in SPDX documents (9f1825e)
  - The `SPDX_CONCLUDED_LICENSE` allows specifying the `hasConcludedLicense` object of individual SBOM packages when using the `create-spdx` class (bb21c6a)
  - The `FIT_MKIMAGE_EXTRA_OPTS` variable allows passing extra options to the `mkimage` command when creating a FIT image with the `kernel-fit-image` class (d925d67)
  - The `FIT_CONF_MAPPINGS` variable allows mapping extra configurations to existing ones or rename an existing configuration in FIT images created with the `kernel-fit-image` class (e30f809)
  - The `UBOOT_CONFIG_FRAGMENTS` and `UBOOT_FRAGMENTS` allow supplying additional configuration fragments to the existing U-Boot configuration. See the definition of the variables for more information, and the documentation of the `uboot-config` class (9e96d3d)
  - The `IMAGE_EXTRA_PARTITION_FILES` allows specifying extra files from the deploy directory (`DEPLOY_DIR_IMAGE`) to install in a WIC partition created with the `extra_partition` plugin (e152607)
  - The `FIT_LOADABLES`, `FIT_LOADABLE_FILENAME`, `FIT_LOADABLE_TYPE`, `FIT_LOADABLE_ARCH`, `FIT_LOADABLE_OS` and `FIT_LOADABLE_LOADADDRESS` variables can be used to specify arbitrary loadables in a FIT image (2535427)
- Global configuration changes:
    - Changes in `DISTRO_FEATURES` default values and how `DISTRO_FEATURES` and `MACHINE_FEATURES` are provided, see *Migration notes for 6.0 (wrynose)* for more information.
    - `base-passwd`: Add a `clock` group as `systemd` version v258 introduces this group to enable applications like `linuxptp` to open clocks without root privileges (aad8493)
    - `lto.inc`: Add a *Clang* specific `LTO` configuration (253da2e)
    - `bitbake.conf`:
      - \* remove `DEBUG_PREFIX_MAP` from `TARGET_LDFLAGS` (1797741)
      - \* The default definition of `TARGET_LDFLAGS` used to contain the value of `DEBUG_PREFIX_MAP`, to fix binary reproducibility issues. This was no longer needed after the originating `GCC` bug was fixed (1797741)
      - \* Switch `BB_SIGNATURE_HANDLER` to `OEEquivHash` and `BB_HASHSERVE` to `auto` by default (5596ea1, 4a38840)
    - The `uninative` class is now enabled by default. This allows reuse of native sstate built on one distro on another (722897f)
    - The `no-static-libs.inc` file, disabling most static libraries in various recipes, is now included by default in the default distro setup (appearing as the `nodistro DISTRO`) (03fc931)
    - The `security_flags.inc` file, adding various security related flags to the default compiler and linker, is now included by default in the default distro setup (appearing as `nodistro DISTRO`) (4c2d64c)
    - The `yocto-space-optimize.inc` file, adding various space optimization tweaks, is now included by default in the default distro setup (appearing as `nodistro DISTRO`) (175fcf9)

- QEMU / runqemu changes:
  - `qemuboot`: Make the tap interface nameserver configurable through `QB_TAP_NAMESERVER` (0e8c258)
  - `qemu`: Disable the `libkeyutils` feature (30cc9f5)
  - `runqemu-extract-sdk`: Support the `tar.zst` format (650bb45)
  - `qemurunner`: Improve `qmp` module detection (a7386d0)
  - `runqemu`: Support `.tar.zst`, `.tar.xz`, `.tar` rootfs archive types (3a6172f)
  - `runqemu`: Allow VNC to be used as a fallback when there is no `DISPLAY` set (df9e9f3)
- Documentation changes:
  - The documentation build now fetches the list of active and inactive versions of the documentation from the remote `releases.json` file. This also applies to the *BitBake* documentation.
- Go changes:
  - `go`: Disable workspaces when building (`GOWORK="off"`) (c52c5e8)
  - `meta-go-toolchain`: Disable support for the `riscv32` and `ppc32` architectures, as this was not supported (f554071)
- Rust changes:
  - Enable dynamic linking with `llvm`. This allows dynamically linking to `libLLVM.so` instead of linking statically (74ba238)
  - Install Rust library sources for `make rustavailable` support (2912ca3)
  - Enable dynamic LLVM linking by default (d0671c3)
  - Enable fully static linking when `TCLIBC` is set to `musl` (75409c6)
- Wic Image Creator changes:
  - `wic/engine`: Fix copying directories into wic image with `ext*` partitions (1ed38af)
  - Re-implement sector-size support (b50d6de)
  - The Wic tool is now maintained in a separate project, no longer part of *OpenEmbedded-Core (OE-Core)*: <https://git.yoctoproject.org/wic/>
  - A new `wicenv` type can be added to `IMAGE_FSTYPES` to place the `.env` file generate by Wic in the deployment directory (`DEPLOY_DIR_IMAGE`) (e4d4970)
- Testing-related changes:
  - `ptest` support was added for the following recipes:
    - \* `libarchive` (6e0bf90)
    - \* `libassuan` (1010abf)
    - \* `libcheck` (1bb06e2)
    - \* `libconfig` (f3e9d13)

- \* `libksba` (f50a200)
- \* `libmd` (4c0a413)
- \* `libpcre2` (a7b79bf)
- \* `libsolv` (f5432d1)
- \* `libyaml` (ed2a345)
- \* `utfcpp` (49314ca)
- `selftests`: Use SHA256 keys for RPM tests (692919b)
- `oeqa`: Open JSON files to parse in a context manager (e96baf5)
- `resulttool`: Add *ptest* support to the JUnit output format (2abe2d7)
- *do\_testimage*: Print last lines of kernel log on test fail (fea3c44)
- `reproducible`: Use the *jQuery* CDN instead of `jquery-native` (d3ee549)
- `selftest`: Test installation of recipes with complex packaging (6f3aab6)
- Add `test_sdk_runqemu` to test the execution of `runqemu` from an SDK (7fbb281)
- Add tests for Rust support in the Linux kernel (01ea2b2, 10dff9f)
- Replace `runltp` with `kirk`, as it became the new official LTP test executor (c1e5ed4)
- *WIC* related tests were updated after `wic` was moved to its own repository and is externally managed (b9e2a2f)
- Utility script changes:classes
  - `bitbake-config-build`: It is now possible to disable all fragments starting with a prefix by issuing `bitbake-config-build disable-fragment <prefix>/` (573695d)
  - `recipetool`: Support PEP639-variant of license key in Python `pyproject.toml` files (9d1a7bb)
  - *buildhistory*:
    - \* Also show renamed directories (9bf2211)
    - \* Fix handling of *RDEPENDS* style strings (b013d62)
  - `create-pull-request`: Keep commit hash to be pulled in cover email (c78f5ae)
  - `yocto-check-layer`: Add messages in `test_readme` assertions (9fe883c)
  - `improve_kernel_cve_report`:
    - \* Sort `kernel_compiled_files` (682e5be)
    - \* Correct the description for fixed version (b76da20)
    - \* Update data if CVE exists (9ea6d92)
    - \* Validate that `cve_details` field exists (80ff490)
  - `oe-pkgdata-util`: improve the `lookup-pkg` error message for *RPROVIDES* packages (46ff3a8)
- BitBake changes:

- bitbake-layers:
  - \* Add a `--show-variants` option to the `show-recipes` subcommand to display *BBCLASSEX-TEND* variants (353d5e9)
  - \* Fix the branch detection method of `layerindex-fetch` (af9dd01)
- bitbake-setup:
  - \* Implement symlinking local sources into builds with the `--use-local-source` option of the `init` subcommand (ed5a3a0)
  - \* Convert `print()` calls to use a *BitBake* logger (6e511d0)
  - \* Correct several scenarios in layer updates (aa15cc7)
  - \* Source in the `git-remote` section can now be specified more simply with the `uri` property, instead of the `remotes` property (7941a5d). For example:
 

```
"bitbake": {
    "git-remote": {
      "uri": "https://git.openembedded.org/bitbake",
      "branch": "master",
      "rev": "master"
    }
  }
```
  - \* Use the internal registry if run from a Git checkout, from a remote *BitBake* repository otherwise (675e907)
  - \* Fragments passed in the `oe-fragments-one-of` property can now contain descriptions (29f2cee)
  - \* Improve the readability of choices during the `bitbake-setup init` command (d970063)
  - \* Enable coloring of the diff outputs when using the `bitbake-setup status` or `bitbake-setup update` commands
  - \* The `bitbake-setup update` now behaves in a non-destructive way: local commits and modifications to layers are taken into account, and the tool will either stop or warn the user that the update is possible or not (2ee3a19)
  - \* Share *Shared State* by default between builds, by adding a definition for `SSTATE_DIR` and `BB_HASHSERVE_DB_DIR` in the `build/conf/auto.conf` file created by `bitbake-setup init` (a70c336)
  - \* Generate config files for VSCode by default, unless `--no-init-vscode` is passed to `bitbake-setup init` (92fd721)
- The `unpack()` function (the one containing the logic of the *do\_unpack* task), can now take an `update` argument to allow updating a Git repository in-place rather than deleting it and re-creating it. An alias function named `unpack_update()` was created for this `unpack` mode. See *The Non-Destructive Update (unpack\_update)* for more information (e7d5e15)
- `cooker`: Use `BB_HASHSERVE_DB_DIR` as hash server database location. If unset, the existing behavior is preserved (b339d05)

- `bitbake-getvar`: Show close matches when no providers are found ([1f8fa7c](#))
- The `GIT_CONFIG_GLOBAL` environment variable will now be taken into account by the Git fetcher, to allow passing a different set of Git configuration options when fetching Git repositories ([4c37844](#))
- When using the `subpath` parameter with the Git fetcher in an `SRC_URI`, properly make the `HEAD` point to the value specified in `SRCREV`.
- Clang/LLVM related changes:
  - `compiler-rt`:
    - \* Remove the need to depend on `libgcc` ([f504b6b](#))
    - \* Always build C runtime (`crt`) files ([56fe42a](#))
  - `libcxx`: Remove GNU runtime from dependencies ([8034509](#))
  - `libcxx/compiler-rt`: Add support for `llvm-libgcc`, a drop-in replacement for `libgcc` and `crt` files ([ed02230](#))
- SPDX-related changes:
  - Output SBOM documents now include recipe metadata ([d999ac4](#))
  - `spdx30_tasks`: Fix `SPDX_CUSTOM_ANNOTATION_VARS` implementation ([52ab3b6](#))
  - `kernel`: Add a task to export the kernel configuration to SPDX ([228a968](#))
  - Add support for exporting the `PACKAGECONFIG` to SPDX ([7ec61ac](#))
  - Add support for package URLs (PURLs) through `SPDX_PACKAGE_URL` ([874b2d3](#))
  - Support only SPDX 3 and removed SPDX 2.2 support. ([12abd05](#))
  - The `create-spdx` class used to include `VEX` statements in the SPDX documents tied to each packages. This is no longer the case, as these statements are now found in the SPDX documents for recipes directly. This was done to decrease the duplication of these statements for packages that were generated by the same recipe.

The output SPDX document for an image recipe will still include the VEX statements, as the SPDX document for the image also include the recipe SPDX metadata.

The inclusion of VEX statements in SPDX documents can be controlled with the `SPDX_INCLUDE_VEX` variable ([d999ac4](#))
- devtool changes:
  - `ide-sdk`:
    - \* Find `bitbake-setup`'s `init-build-env` first, and `oe-init-build-env` if not found ([6ab7e9e](#))
    - \* Add `gdbserver` attach mode support ([1191710](#))
    - \* Support GDB pretty-printing for C++ STL types ([a69e2ba](#))
    - \* Support kernel module development ([aaf15d6](#))
  - Add new patches in correct order when running `devtool finish` ([fa7877d](#))



- Prevent `devtool modify -n` from corrupting Linux kernel Git repos ([d383ea3](#))
- Patchtest-related changes:
  - Code refactoring and improvements ([86d0b22](#), [317ef42](#), [6cdb5cb](#), [ae787b3](#), [a850252](#))
  - Reject `Upstream-Status` after scissors ([2156ef9](#))
- *insane* / *sanity* classes related changes:
  - Reject *TMPDIR* containing redundant slashes to avoid errors in executions of *do\_populate\_sysroot* ([3e72ebe](#))
  - *sanity*: Warn when the *Shared State* cache directory (*SSTATE\_DIR*) is outside of the build directory (*BUILDDIR*), but the *Equivalenza degli Hash* database is inside it ([491de0d](#))
- Security changes:
  - A new document was added to the Yocto Project documentation: *Riferimento di Yocto Project Security*. It is intended to document how to report vulnerabilities to the Yocto Project security team.
- *sbom-cve-check*-related changes:
  - Escape special characters in CPE 2.3 strings ([9dd9c00](#))
- New *PACKAGECONFIG* options for individual recipes:
  - `curl: schannel`
  - `gststreamer1.0-plugins-bad: fdkaac`
  - `gststreamer1.0-plugins-good: qt6`
  - `libinput: lua, libwacom, mtdev`
  - `librepo: sequoia`
  - `mesa: expat, zlib`
  - `openssl: legacy`
  - `opkg: acl, xattr`
  - `orc: hotdoc`
  - `python3: freethreading` (experimental, see [c569901](#))
  - `python3-cryptography: legacy-openssl`
  - `systemd: osc-context`
  - `systemtap: readline`
- systemd related changes:
  - Package `ukify` separately, with the `systemd-ukify` package name ([e924274](#))
- U-Boot related changes:
  - *uboot-config*: Add support for generating the U-Boot initial environment in binary format using *UBOOT\_INITIAL\_ENV\_BINARY* ([cf11b14](#))

- A new way of specifying multiple U-Boot configurations has been added (cd9e730). See *U-Boot configuration flow changes (ref-classes-uboot-config)*
- Miscellaneous changes:
  - curl: Ensure CURL\_CA\_BUNDLE from host environment is respected (545e43a)
  - weston: Add PipeWire as runtime dependency when pipewire is part of *PACKAGECONFIG* (9f52867)
  - uki: Use basename of device trees available via *KERNEL\_DEVICETREE* (27a7fbb)
  - rpcbind: Set the owner of /run/rpcbind to rpc (80e4289)
  - archiver: Remove *WORKDIR* from the patch directory (c99d228)
  - gtk4: Convert to use the *gnomebase* class (fcd5e7c)
  - udev-extraconf: Split automount and autonet into separate packages (udev-extraconf-automount and udev-extraconf-autonet) (08662d7)
  - e2fsprogs: Fix a bug for files larger than 2GB (683a1e7)
  - mesa: Add support for the virtio, gfxstream, hasvk Vulkan drivers (8e7ffdc, 3b56f14)
  - mesa: Drop VDPAU remnants in the recipe after upstream support was removed (3b05f58)
  - cross: Propagate dependencies to outhash, improving *hash equivalence* (267b651)
  - run-postinsts: Propagate exit status to the run-postinsts.service systemd service (7f74d88)
  - freetype: Use *meson* instead of *autotools*\* (7395e4f)
  - wpa-supPLICANT:
    - \* Build with OWE support by default (d16c66b)
    - \* Build with 802.11be support by default (d16c66b)
  - overlayfs: Remove helper unit (623c20f)
  - patch: Show full path when a patch fails to apply (602e28b)
  - kea: Replace keactrl with kea daemons (kea-dhcp\*) in initscripts (7f9d929), and remove keactrl from the recipe (08c3877)
  - initramfs-framework:
    - \* Add handover of PID 1's arguments to modules (a0ab3d1)
    - \* Fix Linux kernel command line parsing when passing in double quotes (f9acaf1)
  - perl: Provide pod2man (in the recipe's *PROVIDES* definition). This is used by many other recipes to produce man pages. This allows existing recipes to explicitly depend on pod2man-native to produce man pages (1d1e55d)
  - build-sysroots: Add sysroot tasks to default build and remove warning (e73f150)
  - Licenses and manifests are now deployed in the SDK when setting *COPY\_LIC\_DIRS* and/or *COPY\_LIC\_MANIFEST*, for both host and target sysroots (f757ae4)
  - openssl: Disable TLS 1.0/1.1 by default (d5501e7)

- python3-cryptography: Disable legacy-openssl feature by default ([1acd199](#))
- openssl: Add support for config snippet includes. This can be done by installing extra configuration files in `${sysconfdir}/ssl/openssl.cnf.d/` ([34bafcf](#))
- busybox:
  - \* Enable SELinux support if `DISTRO_FEATURES` contains `selinux` ([c544f12](#))
  - \* Do not build SUID binary without an applet ([1406f95](#))
- coreutils: `kill` and `uptime` are no longer provided by the recipe ([cedeb95](#))
- tccl8: Skip timing-sensitive *ptests* ([1b93479](#))
- license\_image.bbclass: Report all packages with incompatible license (when using *INCOMPATIBLE\_LICENSE*) ([57fe3e4](#))
- python3: Package all of the compression module into `python3-compression` ([5f34680](#))
- gobject-introspection: Disable cache for the scanner during the *do\_compile* task (`GI_SCANNER_DISABLE_CACHE=1`), to fix an intermittent build failure ([2b55dd1](#))
- *archiver*: Don't try to preserve all attributes when copying files ([6e83136](#))
- *useradd*\*: allow inheriting the class with only *USERADD\_DEPENDS* set, when a recipe only depends on users/groups created by another ([09a901b](#))
- vim: disable *GTK+3* UI by default ([a07763f](#))

## Known Issues in 6.0

Referencing an unset variable in *DISTRO\_FEATURES* causes *DISTRO\_FEATURES\_NATIVE* and *DISTRO\_FEATURES\_NATIVESDK* to be set incorrectly. This leads to confusing errors, such as:

- Nothing PROVIDES 'libseccomp-native'
- Required build target 'glibc' has no buildable providers.

To resolve these errors, ensure that all variables referenced in *DISTRO\_FEATURES* are set. Variables may be set to an empty string if not needed.

A fix for this issue is in progress and should be included in Yocto Project 6.0.1. See Yocto bug [16275](#) for further details.

## Recipe License changes in 6.0

The following changes have been made to the *LICENSE* values set by recipes:

| Recipe(s)                           | Previous value                                                      | New value                                                                                       |
|-------------------------------------|---------------------------------------------------------------------|-------------------------------------------------------------------------------------------------|
| libx-<br>crypt-compat,<br>libxcrypt | LGPL-2.1-only                                                       | LGPL-2.1-only & 0BSD &<br>BSD-3-Clause                                                          |
| libpcre2                            | BSD-3-Clause                                                        | BSD-3-Clause & BSD-2-Clause &<br>MIT                                                            |
| libte-<br>st-fatal-perl             | Artistic-1.0   GPL-1.0-or-later                                     | Artistic-1.0-Perl   GPL-1.<br>0-or-later                                                        |
| python3-cffi                        | MIT                                                                 | MIT-0                                                                                           |
| icu                                 | ICU                                                                 | ICU & MIT                                                                                       |
| iso-code                            | LGPL-2.1-only                                                       | LGPL-2.1-or-later                                                                               |
| ruby                                | Ruby   BSD-2-Clause  <br>BSD-3-Clause   GPL-2.0-only<br>  ISC   MIT | Ruby   BSD-2-Clause  <br>BSD-3-Clause   GPL-2.0-only<br>  ISC   MIT   BSL-1.0   Apa-<br>che-2.0 |

## Security Fixes in 6.0

The following CVEs have been fixed:

| Recipe                | CVE IDs                                                                                                                                                           |
|-----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| avahi                 | CVE-2025-59529, CVE-2026-34933                                                                                                                                    |
| binutils              | CVE-2025-69644, CVE-2025-69647, CVE-2025-69648, CVE-2025-69649,<br>CVE-2025-69650, CVE-2025-69651, CVE-2025-69652, CVE-2026-3441,<br>CVE-2026-3442, CVE-2026-4647 |
| binutils-cross-x86_64 | CVE-2025-69644, CVE-2025-69647, CVE-2025-69648, CVE-2025-69649,<br>CVE-2025-69650, CVE-2025-69651, CVE-2025-69652, CVE-2026-3441,<br>CVE-2026-3442, CVE-2026-4647 |
| binutils-testsuite    | CVE-2025-69644, CVE-2025-69647, CVE-2025-69648, CVE-2025-69649,<br>CVE-2025-69650, CVE-2025-69651, CVE-2025-69652, CVE-2026-3441,<br>CVE-2026-3442, CVE-2026-4647 |
| cargo                 | CVE-2026-39837, CVE-2026-39839, CVE-2026-39840, CVE-2026-39841                                                                                                    |
| cups                  | CVE-2026-34978, CVE-2026-34979, CVE-2026-34980, CVE-2026-34990,<br>CVE-2026-39314, CVE-2026-39316                                                                 |
| ffmpeg                | CVE-2025-69693, CVE-2026-40962                                                                                                                                    |
| glibc                 | CVE-2026-4046, CVE-2026-4437, CVE-2026-4438                                                                                                                       |
| go                    | CVE-2026-27140, CVE-2026-27143, CVE-2026-27144, CVE-2026-32280,<br>CVE-2026-32281, CVE-2026-32282, CVE-2026-32283, CVE-2026-32288,<br>CVE-2026-32289              |
| go-binary-native      | CVE-2026-27140, CVE-2026-27143, CVE-2026-27144, CVE-2026-32280,<br>CVE-2026-32281, CVE-2026-32282, CVE-2026-32283, CVE-2026-32288,<br>CVE-2026-32289              |

continues on next page

Tabella 3 – continua dalla pagina precedente

| Recipe             | CVE IDs                                                                                                                                                             |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| go-cross-x86-64-v3 | CVE-2026-27140, CVE-2026-27143, CVE-2026-27144, CVE-2026-32280, CVE-2026-32281, CVE-2026-32282, CVE-2026-32283, CVE-2026-32288, CVE-2026-32289                      |
| go-runtime         | CVE-2026-27140, CVE-2026-27143, CVE-2026-27144, CVE-2026-32280, CVE-2026-32281, CVE-2026-32282, CVE-2026-32283, CVE-2026-32288, CVE-2026-32289                      |
| gststreamer1.0     | CVE-2026-2920, CVE-2026-2921, CVE-2026-2922, CVE-2026-2923, CVE-2026-3081, CVE-2026-3082, CVE-2026-3083, CVE-2026-3084, CVE-2026-3085, CVE-2026-3086                |
| libarchive         | CVE-2026-5121                                                                                                                                                       |
| libexif            | CVE-2026-40385, CVE-2026-40386                                                                                                                                      |
| libinput           | CVE-2026-35093, CVE-2026-35094                                                                                                                                      |
| libpng             | CVE-2026-33416, CVE-2026-33636                                                                                                                                      |
| libsndfile1        | CVE-2024-50613, CVE-2025-52194                                                                                                                                      |
| libsoup            | CVE-2026-1467, CVE-2026-1536, CVE-2026-1539, CVE-2026-1801, CVE-2026-2443, CVE-2026-3099, CVE-2026-3632, CVE-2026-3633, CVE-2026-3634, CVE-2026-4271, CVE-2026-5119 |

continues on next page

Tabella 3 – continua dalla pagina precedente

| Recipe      | CVE IDs                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| linux-yocto | <p>           CVE-2019-14899, CVE-2021-3714, CVE-2021-3864, CVE-2022-0400,<br/>           CVE-2022-1247, CVE-2022-4543, CVE-2023-3397, CVE-2023-3640,<br/>           CVE-2023-4010, CVE-2023-6238, CVE-2023-6240, CVE-2025-40039,<br/>           CVE-2025-40040, CVE-2025-40082, CVE-2025-40149, CVE-2025-40164,<br/>           CVE-2025-40251, CVE-2025-68211, CVE-2025-68214, CVE-2025-68223,<br/>           CVE-2025-68333, CVE-2025-68340, CVE-2025-68351, CVE-2025-68358,<br/>           CVE-2025-68365, CVE-2025-68725, CVE-2025-68749, CVE-2025-68817,<br/>           CVE-2025-68823, CVE-2025-71071, CVE-2025-71072, CVE-2025-71073,<br/>           CVE-2025-71074, CVE-2025-71075, CVE-2025-71076, CVE-2025-71077,<br/>           CVE-2025-71078, CVE-2025-71079, CVE-2025-71080, CVE-2025-71081,<br/>           CVE-2025-71082, CVE-2025-71083, CVE-2025-71084, CVE-2025-71085,<br/>           CVE-2025-71086, CVE-2025-71087, CVE-2025-71088, CVE-2025-71089,<br/>           CVE-2025-71091, CVE-2025-71093, CVE-2025-71094, CVE-2025-71095,<br/>           CVE-2025-71096, CVE-2025-71097, CVE-2025-71098, CVE-2025-71099,<br/>           CVE-2025-71100, CVE-2025-71101, CVE-2025-71102, CVE-2025-71104,<br/>           CVE-2025-71105, CVE-2025-71107, CVE-2025-71108, CVE-2025-71109,<br/>           CVE-2025-71111, CVE-2025-71112, CVE-2025-71113, CVE-2025-71114,<br/>           CVE-2025-71115, CVE-2025-71116, CVE-2025-71117, CVE-2025-71118,<br/>           CVE-2025-71119, CVE-2025-71120, CVE-2025-71121, CVE-2025-71122,<br/>           CVE-2025-71124, CVE-2025-71125, CVE-2025-71126, CVE-2025-71127,<br/>           CVE-2025-71128, CVE-2025-71129, CVE-2025-71130, CVE-2025-71131,<br/>           CVE-2025-71132, CVE-2025-71133, CVE-2025-71134, CVE-2025-71135,<br/>           CVE-2025-71136, CVE-2025-71137, CVE-2025-71138, CVE-2025-71141,<br/>           CVE-2025-71142, CVE-2025-71143, CVE-2025-71147, CVE-2025-71148,<br/>           CVE-2025-71149, CVE-2025-71150, CVE-2025-71151, CVE-2025-71152,<br/>           CVE-2025-71153, CVE-2025-71154, CVE-2025-71156, CVE-2025-71157,<br/>           CVE-2025-71158, CVE-2025-71160, CVE-2025-71161, CVE-2025-71162,<br/>           CVE-2025-71163, CVE-2025-71180, CVE-2025-71182, CVE-2025-71183,<br/>           CVE-2025-71184, CVE-2025-71185, CVE-2025-71186, CVE-2025-71187,<br/>           CVE-2025-71188, CVE-2025-71189, CVE-2025-71190, CVE-2025-71191,<br/>           CVE-2025-71200, CVE-2025-71201, CVE-2025-71202, CVE-2025-71203,<br/>           CVE-2025-71204, CVE-2025-71220, CVE-2025-71221, CVE-2025-71222,<br/>           CVE-2025-71223, CVE-2025-71225, CVE-2025-71227, CVE-2025-71229,<br/>           CVE-2025-71230, CVE-2025-71231, CVE-2025-71232, CVE-2025-71233,<br/>           CVE-2025-71234, CVE-2025-71235, CVE-2025-71236, CVE-2025-71237,<br/>           CVE-2025-71238, CVE-2026-22976, CVE-2026-22977, CVE-2026-22978,<br/>           CVE-2026-22979, CVE-2026-22980, CVE-2026-22981, CVE-2026-22982,<br/>           CVE-2026-22984, CVE-2026-22985, CVE-2026-22986, CVE-2026-22989,<br/>           CVE-2026-22990, CVE-2026-22991, CVE-2026-22992, CVE-2026-22993,<br/>           CVE-2026-22994, CVE-2026-22996, CVE-2026-22997, CVE-2026-22998,<br/>           CVE-2026-22999, CVE-2026-23000, CVE-2026-23001, CVE-2026-23002,<br/>           CVE-2026-23003, CVE-2026-23005, CVE-2026-23006, CVE-2026-23007,<br/>           CVE-2026-23008, CVE-2026-23009, CVE-2026-23010, CVE-2026-23011,<br/>           CVE-2026-23013, CVE-2026-23015, CVE-2026-23017, CVE-2026-23018,<br/>           CVE-2026-23019, CVE-2026-23020, CVE-2026-23021, CVE-2026-23023,<br/>           CVE-2026-23025, CVE-2026-23026, CVE-2026-23060, CVE-2026-23061,<br/>           CVE-2026-23062, CVE-2026-23063, CVE-2026-23064, CVE-2026-23065,         </p> |

Tabella 3 – continua dalla pagina precedente

| Recipe             | CVE IDs                                                                                                                                        |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| mesa               | CVE-2026-40393                                                                                                                                 |
| nfs-utils          | CVE-2025-12801                                                                                                                                 |
| nghttp2            | CVE-2026-27135                                                                                                                                 |
| openssh            | CVE-2026-35414                                                                                                                                 |
| python3            | CVE-2026-4519                                                                                                                                  |
| python3-requests   | CVE-2026-25645                                                                                                                                 |
| qemu               | CVE-2024-6519                                                                                                                                  |
| qemu-system-native | CVE-2024-6519                                                                                                                                  |
| sqlite3            | CVE-2025-70873                                                                                                                                 |
| systemd-boot       | CVE-2026-29111, CVE-2026-40226                                                                                                                 |
| vim                | CVE-2026-28417, CVE-2026-28418, CVE-2026-28419, CVE-2026-28420, CVE-2026-28421, CVE-2026-28422, CVE-2026-33412, CVE-2026-34714, CVE-2026-35177 |
| xz                 | CVE-2026-34743                                                                                                                                 |

## Recipe Upgrades in 6.0

The following recipes have been upgraded:

| Recipe               | Previous version(s) | New version(s) |
|----------------------|---------------------|----------------|
| acpica               | 20250807            | 20251212       |
| adwaita-icon-theme   | 48.0                | 49.0           |
| alsa-lib             | 1.2.14              | 1.2.15.3       |
| alsa-tools           | 1.2.14              | 1.2.15         |
| alsa-ucm-conf        | 1.2.14              | 1.2.15.3       |
| alsa-utils           | 1.2.14              | 1.2.15.2       |
| appstream            | 1.0.6               | 1.1.2          |
| aspell               | 0.60.8.1            | 0.60.8.2       |
| at-spi2-core         | 2.56.4              | 2.60.0         |
| autoconf             | 2.72                | 2.73           |
| barebox              | 2025.09.3           | 2026.04.0      |
| barebox-tools        | 2025.09.3           | 2026.04.0      |
| base-passwd          | 3.6.7               | 3.6.8          |
| bash-completion      | 2.16.0              | 2.17.0         |
| bind                 | 9.20.15             | 9.20.22        |
| binutils             | 2.45.1+git          | 2.46           |
| binutils-cross       | 2.45.1+git          | 2.46           |
| binutils-cross-canac | 2.45.1+git          | 2.46           |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe                 | Previous version(s)    | New version(s)         |
|------------------------|------------------------|------------------------|
| binu-tils-crosssdk     | 2.45.1+git             | 2.46                   |
| binu-tils-testsuite    | 2.45.1+git             | 2.46                   |
| bluez5                 | 5.84                   | 5.86                   |
| boost                  | 1.89.0                 | 1.90.0                 |
| boo-st-build-native    | 1.89.0                 | 1.90.0                 |
| btrfs-tools            | 6.16                   | 6.19.1                 |
| cargo                  | 1.90.0                 | 1.94.1                 |
| cargo-c                | 0.10.16+cargo-0.91.0   | 0.10.21+cargo-0.95.0   |
| ccache                 | 4.12.3                 | 4.13.2                 |
| clang                  | 21.1.7                 | 22.1.3                 |
| cmake                  | 4.1.2                  | 4.3.1                  |
| cmake-native           | 4.1.2                  | 4.3.1                  |
| compiler-rt            | 21.1.7                 | 22.1.3                 |
| compi-ler-rt-sanitizer | 21.1.7                 | 22.1.3                 |
| connman                | 1.45                   | 2.0                    |
| coreutils              | 9.7                    | 9.10                   |
| createrepo-c           | 1.2.1                  | 1.2.3                  |
| cross-localedef        | 2.42+git               | 2.43+git               |
| crypto-dev-linux       | 1.14 (135cbff90af2...) | 1.14 (08644db02d43...) |
| crypto-dev-module      | 1.14 (135cbff90af2...) | 1.14 (08644db02d43...) |
| crypto-dev-tests       | 1.14 (135cbff90af2...) | 1.14 (08644db02d43...) |
| cups                   | 2.4.15                 | 2.4.16                 |
| curl                   | 8.17.0                 | 8.19.0                 |
| dhcpcd                 | 10.2.4                 | 10.3.0                 |
| diffoscope             | 306                    | 314                    |
| dmidecode              | 3.6                    | 3.7                    |
| dnf                    | 4.23.0                 | 4.24.0                 |
| dos2unix               | 7.5.2                  | 7.5.4                  |
| dpkg                   | 1.22.21                | 1.23.7                 |
| dropbear               | 2025.88                | 2025.89                |
| e2fsprogs              | 1.47.3                 | 1.47.4                 |
| ed                     | 1.22.2                 | 1.22.5                 |
| elfutils               | 0.193                  | 0.194                  |
| ell                    | 0.80                   | 0.83                   |

continues on next page



Tabella 4 – continua dalla pagina precedente

| Recipe                   | Previous version(s)     | New version(s)          |
|--------------------------|-------------------------|-------------------------|
| enchant2                 | 2.8.14                  | 2.8.15                  |
| epiphany                 | 48.5                    | 49.7                    |
| erofs-utils              | 1.8.10                  | 1.9.1                   |
| ethtool                  | 6.15                    | 6.19                    |
| expat                    | 2.7.4                   | 2.7.5                   |
| fastfloat                | 8.0.2                   | 8.2.4                   |
| ffmpeg                   | 8.0                     | 8.0.1                   |
| file                     | 5.46                    | 5.47                    |
| fmt                      | 11.2.0                  | 12.1.0                  |
| font-alias               | 1.0.5                   | 1.0.6                   |
| freetype                 | 2.13.3                  | 2.14.3                  |
| gawk                     | 5.3.2                   | 5.4.0                   |
| gdb                      | 16.3                    | 17.1                    |
| gdb-cross                | 16.3                    | 17.1                    |
| gdb-cross-canadi         | 16.3                    | 17.1                    |
| gdk-pixbuf               | 2.42.12                 | 2.44.5                  |
| gettext                  | 0.26                    | 1.0                     |
| get-<br>text-minimal-nat | 0.26                    | 1.0                     |
| gi-docgen                | 2025.4                  | 2026.1                  |
| git                      | 2.51.0                  | 2.53.0                  |
| glew                     | 2.2.0                   | 2.3.1                   |
| glib-2.0                 | 2.86.4                  | 2.88.0                  |
| glib-2.<br>0-initial     | 2.86.4                  | 2.88.0                  |
| glibc                    | 2.42+git                | 2.43+git                |
| glibc-locale             | 2.42+git                | 2.43+git                |
| glibc-mtrace             | 2.42+git                | 2.43+git                |
| glibc-scripts            | 2.42+git                | 2.43+git                |
| glibc-testsuite          | 2.42+git                | 2.43+git                |
| glslang                  | 1.4.328.1               | 1.4.341.0               |
| gn                       | 0+git (81b24e01531e...) | 0+git (9d19a7870add...) |
| gnu-efi                  | 4.0.2                   | 4.0.4                   |
| gnupg                    | 2.5.11                  | 2.5.17                  |
| gnutls                   | 3.8.10                  | 3.8.12                  |
| go                       | 1.25.9                  | 1.26.2                  |
| go-binary-native         | 1.25.9                  | 1.26.2                  |
| go-cross-canadi          | 1.25.9                  | 1.26.2                  |
| go-cross-core2-3         | 1.25.9                  | 1.26.2                  |
| go-crosssdk              | 1.25.9                  | 1.26.2                  |
| go-helloworld            | 0.1 (8b405629c4a5...)   | 0.1 (7f05d217867b...)   |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe           | Previous version(s)       | New version(s)            |
|------------------|---------------------------|---------------------------|
| go-runtime       | 1.25.9                    | 1.26.2                    |
| gob-             | 1.84.0                    | 1.86.0                    |
| ject-introspecti |                           |                           |
| groff            | 1.23.0                    | 1.24.0                    |
| grub             | 2.12                      | 2.14                      |
| grub-efi         | 2.12                      | 2.14                      |
| gset-            | 48.0                      | 50.0                      |
| tings-desktop-sc |                           |                           |
| gst-devtools     | 1.26.7                    | 1.28.2                    |
| gst-examples     | 1.26.7                    | 1.28.2                    |
| gststreamer1.0   | 1.26.7                    | 1.28.2                    |
| gststreamer1.    | 1.26.7                    | 1.28.2                    |
| 0-libav          |                           |                           |
| gststreamer1.    | 1.26.7                    | 1.28.2                    |
| 0-plugins-bad    |                           |                           |
| gststreamer1.    | 1.26.7                    | 1.28.2                    |
| 0-plugins-base   |                           |                           |
| gststreamer1.    | 1.26.7                    | 1.28.2                    |
| 0-plugins-good   |                           |                           |
| gststreamer1.    | 1.26.7                    | 1.28.2                    |
| 0-plugins-ugly   |                           |                           |
| gststreamer1.    | 1.26.7                    | 1.28.2                    |
| 0-python         |                           |                           |
| gststreamer1.    | 1.26.7                    | 1.28.2                    |
| 0-rtsp-server    |                           |                           |
| gtk-doc          | 1.34.0                    | 1.35.1                    |
| gtk4             | 4.18.6                    | 4.22.1                    |
| harfbuzz         | 11.4.5                    | 12.3.2                    |
| hwdata           | 0.399                     | 0.405                     |
| hwlatdetect      | 2.9                       | 2.10                      |
| icu              | 77-1                      | 78.3                      |
| ifupdown         | 0.8.44                    | 0.8.45                    |
| igt-gpu-tools    | 2.1                       | 2.3                       |
| inetutils        | 2.6                       | 2.7                       |
| iproute2         | 6.16.0                    | 6.19.0                    |
| iptables         | 1.8.11                    | 1.8.13                    |
| iso-codes        | 4.18.0                    | 4.20.1                    |
| kbd              | 2.8.0                     | 2.9.0                     |
| kea              | 3.0.1                     | 3.0.3                     |
| kern-tools-nativ | 0.3+git (f589e1df2325...) | 0.3+git (a4a362d9f4f0...) |
| kexec-tools      | 2.0.31                    | 2.0.32                    |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe              | Previous version(s)         | New version(s)              |
|---------------------|-----------------------------|-----------------------------|
| kmscube             | 0.0.1+git (2c1f2646c5e5...) | 0.0.1+git (f60e50e887d3...) |
| less                | 679                         | 692                         |
| libadwaita          | 1.7.6                       | 1.8.4                       |
| libarchive          | 3.8.6                       | 3.8.7                       |
| libatomic-ops       | 7.8.4                       | 7.10.0                      |
| libcap              | 2.76                        | 2.77                        |
| libcap-ng           | 0.8.5                       | 0.9.1                       |
| libcap-ng-python    | 0.8.5                       | 0.9.1                       |
| libclc              | 21.1.7                      | 22.1.3                      |
| libcomps            | 0.1.22                      | 0.1.24                      |
| libcxx              | 21.1.7                      | 22.1.3                      |
| libdi-splay-info    | 0.2.0                       | 0.3.0                       |
| libdnf              | 0.74.0                      | 0.75.0                      |
| libdrm              | 2.4.125                     | 2.4.131                     |
| libedit             | 20250104-3.1                | 20251016-3.1                |
| libevdev            | 1.13.5                      | 1.13.6                      |
| libexif             | 0.6.25                      | 0.6.26                      |
| libfontenc          | 1.1.8                       | 1.1.9                       |
| libgcrypt           | 1.11.2                      | 1.12.1                      |
| libgit2             | 1.9.1                       | 1.9.2                       |
| libgloss            | 4.5.0+git                   | 4.6.0+git                   |
| libgpg-error        | 1.56                        | 1.59                        |
| libinput            | 1.29.1                      | 1.30.2                      |
| libjpeg-turbo       | 3.1.2                       | 3.1.3                       |
| libksba             | 1.6.7                       | 1.6.8                       |
| libnl               | 3.11.0                      | 3.12.0                      |
| libnotify           | 0.8.6                       | 0.8.8                       |
| libpam              | 1.7.1                       | 1.7.2                       |
| libpciaccess        | 0.18.1                      | 0.19                        |
| libpcre2            | 10.46                       | 10.47                       |
| libproxy            | 0.5.10                      | 0.5.12                      |
| librsvg             | 2.61.0                      | 2.61.3                      |
| libsolv             | 0.7.35                      | 0.7.36                      |
| libstd-rs           | 1.90.0                      | 1.94.1                      |
| libtasn1            | 4.20.0                      | 4.21.0                      |
| libte-st-fatal-perl | 0.017                       | 0.018                       |
| libtirpc            | 1.3.6                       | 1.3.7                       |
| libtraceevent       | 1.8.4                       | 1.9.0                       |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe                  | Previous version(s)      | New version(s) |
|-------------------------|--------------------------|----------------|
| libubootenv             | 0.3.6                    | 0.3.7          |
| libunistring            | 1.3                      | 1.4.2          |
| liburcu                 | 0.15.3                   | 0.15.6         |
| libuv                   | 1.51.0                   | 1.52.1         |
| libva                   | 2.22.0                   | 2.23.0         |
| libva-initial           | 2.22.0                   | 2.23.0         |
| libva-utils             | 2.22.0                   | 2.23.0         |
| libx11                  | 1.8.12                   | 1.8.13         |
| li-<br>bx11-compose-dat | 1.8.4                    | 1.8.12         |
| libxcomposite           | 0.4.6                    | 0.4.7          |
| libxcrypt               | 4.4.38                   | 4.5.2          |
| libx-<br>crypt-compat   | 4.4.38                   | 4.5.2          |
| libxdamage              | 1.1.6                    | 1.1.7          |
| libxext                 | 1.3.6                    | 1.3.7          |
| libxinerama             | 1.1.5                    | 1.1.6          |
| libxkbcommon            | 1.11.0                   | 1.13.1         |
| libxkbfile              | 1.1.3                    | 1.2.0          |
| libxml2                 | 2.14.6                   | 2.15.2         |
| libxmu                  | 1.2.1                    | 1.3.1          |
| libxpm                  | 3.5.17                   | 3.5.18         |
| libxrandr               | 1.5.4                    | 1.5.5          |
| libxslt                 | 1.1.43                   | 1.1.45         |
| libxvmc                 | 1.0.14                   | 1.0.15         |
| libxxf86vm              | 1.1.6                    | 1.1.7          |
| lighttpd                | 1.4.81                   | 1.4.82         |
| linux-firmware          | 20251111                 | 20260410       |
| li-<br>nux-libc-headers | 6.17                     | 6.18           |
| linux-yocto             | 6.12.69+git, 6.16.11+git | 6.18.24+git    |
| li-<br>nux-yocto-dev    | 6.18+git                 | 7.0+git        |
| linux-yocto-rt          | 6.12.69+git, 6.16.11+git | 6.18.24+git    |
| li-<br>nux-yocto-tiny   | 6.12.69+git, 6.16.11+git | 6.18.24+git    |
| lld                     | 21.1.7                   | 22.1.3         |
| lldb                    | 21.1.7                   | 22.1.3         |
| llvm                    | 21.1.7                   | 22.1.3         |
| ll-<br>vm-tblgen-native | 21.1.7                   | 22.1.3         |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe               | Previous version(s)       | New version(s)            |
|----------------------|---------------------------|---------------------------|
| lsof                 | 4.99.5                    | 4.99.6                    |
| ltp                  | 20250930                  | 20260130                  |
| lttng-modules        | 2.14.3                    | 2.14.4                    |
| lttng-tools          | 2.14.0                    | 2.14.1                    |
| lua                  | 5.4.8                     | 5.5.0                     |
| lzlib                | 1.15                      | 1.16                      |
| m4                   | 1.4.20                    | 1.4.21                    |
| m4-native            | 1.4.20                    | 1.4.21                    |
| makedumpfile         | 1.7.7                     | 1.7.8                     |
| man-pages            | 6.15                      | 6.17                      |
| mdadm                | 4.4                       | 4.6                       |
| mesa                 | 25.2.8                    | 26.0.5                    |
| mesa-gl              | 25.2.8                    | 26.0.5                    |
| meson                | 1.9.1                     | 1.10.2                    |
| mpg123               | 1.33.2                    | 1.33.4                    |
| msmtp                | 1.8.31                    | 1.8.32                    |
| mtt-utils            | 2.3.0                     | 2.3.1                     |
| musl                 | 1.2.5+git                 | 1.2.6+git                 |
| nasm                 | 2.16.03                   | 3.01                      |
| ncurses              | 6.5                       | 6.6                       |
| newlib               | 4.5.0+git                 | 4.6.0+git                 |
| nfs-utils            | 2.8.4                     | 2.8.7                     |
| nghttp2              | 1.66.0                    | 1.68.1                    |
| ninja                | 1.13.1                    | 1.13.2                    |
| ofono                | 2.18                      | 2.19                      |
| openmp               | 21.1.7                    | 22.1.3                    |
| opensbi              | 1.7                       | 1.8.1                     |
| openssh              | 10.2p1                    | 10.3p1                    |
| opkg                 | 0.8.0                     | 0.9.0                     |
| orc                  | 0.4.41                    | 0.4.42                    |
| ovmf                 | edk2-stable202508         | edk2-stable202511         |
| p11-kit              | 0.25.5                    | 0.26.2                    |
| perl                 | 5.40.2                    | 5.42.0                    |
| perlcross            | 1.6.2                     | 1.6.4                     |
| picolibc             | 1.8.6+git                 | 1.8.11+git                |
| pico-libc-helloworld | 1.8.6+git                 | 1.8.11+git                |
| procps               | 4.0.5                     | 4.0.6                     |
| pseudo               | 1.9.3+git                 | 1.9.5                     |
| puzzles              | 0.0+git (a7c7826bce5c...) | 0.0+git (ecb576fb2a0a...) |
| python3              | 3.13.12                   | 3.14.4                    |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe               | Previous version(s) | New version(s) |
|----------------------|---------------------|----------------|
| python3-attrs        | 25.3.0              | 25.4.0         |
| python3-babel        | 2.17.0              | 2.18.0         |
| python3-bcrypt       | 4.3.0               | 5.0.0          |
| py-thon3-beartype    | 0.21.0              | 0.22.9         |
| python3-build        | 1.3.0               | 1.4.0          |
| python3-calver       | 2025.04.17          | 2025.10.20     |
| py-thon3-certifi     | 2025.8.3            | 2026.2.25      |
| python3-cffi         | 1.17.1              | 2.0.0          |
| py-thon3-chardet     | 5.2.0               | 6.0.0.post1    |
| python3-click        | 8.2.2               | 8.3.1          |
| py-thon3-cryptogra   | 45.0.7              | 46.0.5         |
| py-thon3-cryptogra   | 45.0.7              | 46.0.5         |
| python3-cython       | 3.1.3               | 3.2.4          |
| py-thon3-dbusmock    | 0.37.0              | 0.38.1         |
| py-thon3-docutils    | 0.22                | 0.22.4         |
| py-thon3-dtschema    | 2025.8              | 2025.12        |
| py-thon3-hatchling   | 1.27.0              | 1.29.0         |
| py-thon3-hypothesis  | 6.142.2             | 6.151.9        |
| py-thon3-imagesize   | 1.4.1               | 2.0.0          |
| py-thon3-iniconfig   | 2.1.0               | 2.3.0          |
| py-thon3-jjsonschema | 4.25.1              | 4.26.0         |
| py-thon3-markdown    | 3.9                 | 3.10.2         |
| py-thon3-markupsafe  | 3.0.2               | 3.0.3          |
| py-thon3-maturin     | 1.9.4               | 1.12.4         |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe               | Previous version(s) | New version(s) |
|----------------------|---------------------|----------------|
| py-thon3-meson-pytl  | 0.18.0              | 0.19.0         |
| python3-numpy        | 2.3.4               | 2.4.3          |
| py-thon3-packaging   | 25.0                | 26.0           |
| py-thon3-pathspect   | 0.12.1              | 1.0.4          |
| python3-pbr          | 7.0.1               | 7.0.3          |
| python3-pdm          | 2.25.9              | 2.26.6         |
| py-thon3-pdm-backer  | 2.4.5               | 2.4.7          |
| py-thon3-pdm-build-  | 0.3.5               | 0.3.7          |
| python3-pip          | 25.2                | 26.0.1         |
| py-thon3-poetry-cor  | 2.1.3               | 2.3.1          |
| python3-psutil       | 7.0.0               | 7.2.2          |
| python3-pyasnl       | 0.6.1               | 0.6.2          |
| py-thon3-pycairo     | 1.28.0              | 1.29.0         |
| py-thon3-pycparser   | 2.22                | 3.0            |
| py-thon3-pygobject   | 3.52.3              | 3.56.1         |
| py-thon3-pyopenssl   | 25.1.0              | 26.0.0         |
| py-thon3-pyparsing   | 3.2.4               | 3.3.2          |
| py-thon3-pyproject-  | 0.9.1               | 0.11.0         |
| python3-pytest       | 8.4.2               | 9.0.2          |
| py-thon3-pytest-suk  | 0.14.2              | 0.15.0         |
| python3-pytz         | 2025.2              | 2026.1         |
| python3-pyyaml       | 6.0.2               | 6.0.3          |
| python3-rdflib       | 7.1.4               | 7.6.0          |
| py-thon3-rpds-py     | 0.27.1              | 0.30.0         |
| py-thon3-ruamel-yaml | 0.18.15             | 0.19.1         |
| python3-scons        | 4.9.1               | 4.10.1         |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe                     | Previous version(s)   | New version(s)        |
|----------------------------|-----------------------|-----------------------|
| py-thon3-setuptools        | 80.9.0                | 82.0.1                |
| py-thon3-setuptools        | 8.3.1                 | 9.2.2                 |
| python3-sphinx             | 8.2.1                 | 9.1.0                 |
| py-thon3-sphinx-rtc        | 3.0.2                 | 3.1.0                 |
| py-thon3-testtools         | 2.7.2                 | 2.8.7                 |
| py-thon3-trove-classifiers | 2025.9.11.17          | 2026.1.14.14          |
| py-thon3-unittest-asyncio  | 0.3                   | 0.4                   |
| py-thon3-uritools          | 5.0.0                 | 6.0.1                 |
| py-thon3-urllib3           | 2.5.0                 | 2.6.3                 |
| py-thon3-wcwidth           | 0.2.13                | 0.6.0                 |
| py-thon3-webcolors         | 24.11.1               | 25.10.0               |
| py-thon3-websockets        | 15.0.1                | 16.0                  |
| python3-wheel              | 0.46.1                | 0.46.3                |
| py-thon3-xmltodict         | 0.15.1                | 1.0.4                 |
| py-thon3-yamllint          | 1.37.1                | 1.38.0                |
| qemu                       | 10.0.6                | 10.2.0                |
| qemu-native                | 10.0.6                | 10.2.0                |
| qemu-system-native         | 10.0.6                | 10.2.0                |
| quota                      | 4.10                  | 4.11                  |
| re2c                       | 4.3                   | 4.4                   |
| repo                       | 2.58                  | 2.61.1                |
| resolvconf                 | 1.93                  | 1.94                  |
| rgb                        | 1.1.0                 | 1.1.1                 |
| rpm-sequoia                | 1.9.0                 | 1.10.1                |
| rpm-sequoia-crypt          | git (ae1df75b1155...) | git (f3f5fa454345...) |
| rt-tests                   | 2.9                   | 2.10                  |
| ruby                       | 3.4.5                 | 4.0.2                 |

continues on next page



Tabella 4 – continua dalla pagina precedente

| Recipe                     | Previous version(s) | New version(s) |
|----------------------------|---------------------|----------------|
| rust                       | 1.90.0              | 1.94.1         |
| ru-<br>st-cross-canadie    | 1.90.0              | 1.94.1         |
| sbc                        | 2.1                 | 2.2            |
| scdoc                      | 1.11.3              | 1.11.4         |
| seatd                      | 0.9.1               | 0.9.3          |
| shaderc                    | 2025.3              | 2026.1         |
| shadow                     | 4.18.0              | 4.19.4         |
| socat                      | 1.8.0.3             | 1.8.1.1        |
| spirv-headers              | 1.4.328.1           | 1.4.341.0      |
| spirv-llvm-trans           | 21.1.1              | 22.1.1         |
| spirv-tools                | 1.4.328.1           | 1.4.341.0      |
| sqlite3                    | 3.48.0              | 3.51.3         |
| squashfs-tools             | 4.7.2               | 4.7.5          |
| strace                     | 6.16                | 6.19           |
| stress-ng                  | 0.19.04             | 0.20.01        |
| swig                       | 4.3.1               | 4.4.1          |
| sysstat                    | 12.7.8              | 12.7.9         |
| systemd                    | 257.8               | 259.5          |
| systemd-boot               | 257.8               | 259.5          |
| syste-<br>md-boot-native   | 257.8               | 259.5          |
| syste-<br>md-systemctl-nat | 257.8               | 259.5          |
| systemtap                  | 5.3                 | 5.4            |
| system-<br>tap-native      | 5.3                 | 5.4            |
| taglib                     | 2.1.1               | 2.2.1          |
| tcl                        | 9.0.2               | 9.0.3          |
| texinfo                    | 7.2                 | 7.3            |
| ttyrun                     | 2.38.0              | 2.41.0         |
| u-boot                     | 2025.10             | 2026.01        |
| u-boot-tools               | 2025.10             | 2026.01        |
| usbutils                   | 018                 | 019            |
| utfcpp                     | 4.0.6               | 4.0.9          |
| util-linux                 | 2.41.1              | 2.41.3         |
| util-linux-libuv           | 2.41.1              | 2.41.3         |
| valgrind                   | 3.25.1              | 3.26.0         |
| vim                        | 9.1.1683            | 9.2.0340       |
| vim-tiny                   | 9.1.1683            | 9.2.0340       |
| virglrenderer              | 1.1.1               | 1.2.0          |

continues on next page

Tabella 4 – continua dalla pagina precedente

| Recipe                   | Previous version(s)         | New version(s)              |
|--------------------------|-----------------------------|-----------------------------|
| vte                      | 0.82.1                      | 0.82.2                      |
| vulkan-headers           | 1.4.328.1                   | 1.4.341.0                   |
| vulkan-loader            | 1.4.328.1                   | 1.4.341.0                   |
| vulkan-samples           | git (d27205d14d01...)       | git (fa2cf45adde0...)       |
| vulkan-tools             | 1.4.328.1                   | 1.4.341.0                   |
| vul-<br>kan-utility-libr | 1.4.328.1                   | 1.4.341.0                   |
| vul-<br>kan-validation-l | 1.4.328.1                   | 1.4.341.0                   |
| vulkan-volk              | 1.4.328.1                   | 1.4.341.0                   |
| way-<br>land-protocols   | 1.45                        | 1.47                        |
| wayland-utils            | 1.2.0                       | 1.3.0                       |
| webkitgtk                | 2.50.4                      | 2.50.6                      |
| weston                   | 14.0.2                      | 15.0.0                      |
| wpebackend-fdo           | 1.16.0                      | 1.16.1                      |
| x264                     | r3039+git (31e19f92f00c...) | r3039+git (0480cb05fa18...) |
| xauth                    | 1.1.4                       | 1.1.5                       |
| xcb-util-cursor          | 0.1.5                       | 0.1.6                       |
| xeyes                    | 1.3.0                       | 1.3.1                       |
| xkbcomp                  | 1.4.7                       | 1.5.0                       |
| xkey-<br>board-config    | 2.45                        | 2.47                        |
| xorgproto                | 2024.1                      | 2025.1                      |
| xserver-xorg             | 21.1.18                     | 21.1.21                     |
| xwayland                 | 24.1.8                      | 24.1.9                      |
| xz                       | 5.8.1                       | 5.8.2                       |
| zlib                     | 1.3.1                       | 1.3.2                       |

## Contributors to 6.0

Thanks to the following people who contributed to this release:

- Adam Blank
- Adam Duskett
- Adarsh Jagadish Kamini
- Aditya Kurdunkar
- Adrian Freihofer
- Ahmad Fatoum
- Alejandro Hernandez Samaniego

- Aleksandar Nikolic
- Alexander Kanavin
- Alexander Sverdlin
- Alex Bradbury
- Alex Kiernan
- Amaury Couderc
- Andrej Kozemcak
- Anibal Limon
- Ankur Tyagi
- Antonin Godard
- Ashish Kumar Mishra
- Ashish Sharma
- BELHADJ SALEM Talel
- Benjamin Robin
- Bruce Ashfield
- Changqing Li
- Chen Qi
- Clement Faure
- Colin Pinnell McAllister
- Corentin Guillevic
- Daiane Angolini
- Daniel Dragomir
- Daniel Turull
- Dan McGregor
- Deepesh Varatharajan
- Dmitry Baryshkov
- Dragomir, Daniel
- El Mehdi YOUNES
- Enrico Jöns
- Ernst Persson
- Etienne Cordonnier
- Fabio Berton

- Fabio Estevam
- Favazza, Samuele
- Florian Schmaus
- Francesco Valla
- Franz Schnyder
- Germann, Bastian
- Guðni Már Gilbert
- Gyorgy Sarvari
- Haiqing Bai
- Harish Sadineni
- Hemanth Kumar M D
- Het Patel
- Hiago De Franco
- Himanshu Jadon
- hongxu
- Hongxu Jia
- Jaeyoon Jung
- Jan Luebbe
- Jan Vermaete
- Jason Schonberg
- Javier Tia
- Jiaying Song
- Jinfeng Wang
- João Marcos Costa
- Jörg Sommer
- Jose Quaresma
- Joshua Watt
- Kai Kang
- Kamel Bouhara
- Kavinaya S
- Ken Kurematsu
- Khai Dang

- Khalifa Rouis
- Khem Raj
- Koen Kooi
- Kory Maincent
- Kristiyan Chakarov
- Krupal Ka Patel
- Lee Chee Yang
- Leon Anavi
- Le Qi
- Liu Yiding
- Livin Sunny
- Liyin Zhang
- Logan Gallois
- Louis Rannou
- Lucas Stach
- Luka Krstic
- Mahesh Angadi
- Mark Hatle
- Mark-Pk Tsai
- Markus Volk
- mark.yang
- Martin Jansa
- Martin Schwan
- Mathieu Dubois-Briand
- Matt Madison
- Maxin B. John
- Maxin John
- Max Krummenacher
- Miaoqing Pan
- Michael Arndt
- Michael Halstead
- Michael Opdenacker

- Michal Sieron
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Miroslav Cernak
- Mohammad Rafi Shaik
- Mohammad Rahimi
- Moritz Haase
- Naftaly RALAMBOARIVONY
- Naman Jain
- Nikhil R
- Niko Mauno
- Nora Schiffer
- Osama Abdelkader
- Patrick Vogelaar
- Patrick Wicki
- Paul Barker
- Pavel Löbl
- Peter Bergin
- Peter de Ridder
- Peter Kjellerstedt
- Peter Marko
- Peter Tatrai
- Philip Lorenz
- Pierre-Loup GOSSE
- Piotr Buliński
- Pratik Farkase
- Quentin Schulz
- Randolph Sapp
- Randy MacLeod
- Ricardo Salveti
- Ricardo Simoes

- Ricardo Ungerer
- Richard Purdie
- Robert Joslyn
- Robert P. J. Day
- Robert Yang
- Rob Woolley
- Ross Burton
- Rouven Rastetter
- Ryan Eatmon
- Sam Povilus
- Samuli Piippo
- Sandeep Gundlupet Raju
- Scott Murray
- Shaik Moin
- Shotaro Uchida
- Stefano Babic
- Stefano Tondo
- Sunil Dora
- sven.kalmbach
- Swami
- Telukula Jeevan Kumar Sahu
- Theo GAIGE
- Thomas Perrot
- Tim Orling
- Tom Geelen
- Trevor Gamblin
- Trevor Woerner
- Ulrich Ölmann
- Uwe Kleine-König
- Veeresh Kadasani
- Victor Kamensky
- Vijay Anusuri

- Viswanath Kraleti
- Vivek Puar
- Vyacheslav Yurkov
- Wang Mingyu
- Weisser, Pascal
- Xiangyu Chen
- Yanis BINARD
- Yann Dirson
- Yannic Moog
- Yash Gupta
- Yash Shinde
- Yasir Al-Latifi
- Yiding Liu
- Yi Zhao
- Yoann Congal
- Yongxin Liu
- Zhangfei Gao
- Zhang Peng
- Zk47T
- Zoltán Böszörményi

## Repositories / Downloads for Yocto-6.0

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [wrynose](#)
- Tag: [yocto-6.0](#)
- Git Revision: [eb74fd9e5e579a65e8872d1a73b51e77b14f63](#)
- Release Artefact: [yocto-docs-eb74fd9e5e579a65e8872d1a73b51e77b14f63](#)
- sha: [50d7391b4b4d169649a5628a8f367443eb03fb78faa813b9c20d5214e49ce782](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0/yocto-docs-eb74fd9e5e579a65e8872d1a73b51e77b14f63.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0/yocto-docs-eb74fd9e5e579a65e8872d1a73b51e77b14f63.tar.bz2>



#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: wrynose
- Tag: yocto-6.0
- Git Revision: 42fa856a00ac16b2a7a83d7ecfa60a5be192b16c
- Release Artefact: oecore-42fa856a00ac16b2a7a83d7ecfa60a5be192b16c
- sha: 14abd19071d1b31737f5d3946182f21825e0a7121468054bbaa68f207b018fb6
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0/oecore-42fa856a00ac16b2a7a83d7ecfa60a5be192b16c.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0/oecore-42fa856a00ac16b2a7a83d7ecfa60a5be192b16c.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: wrynose
- Tag: yocto-6.0
- Git Revision: 904846ae078ee20de073040ebb77c86e19250f56
- Release Artefact: meta-yocto-904846ae078ee20de073040ebb77c86e19250f56
- sha: d3470939772339d2d70a2bbdd4e01563357c376fdb496d5515a1f96bce4e2ea2
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0/meta-yocto-904846ae078ee20de073040ebb77c86e19250f56.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0/meta-yocto-904846ae078ee20de073040ebb77c86e19250f56.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: wrynose
- Tag: yocto-6.0
- Git Revision: a4ba674d6a0a17e4c0bc4c11bbb9d0ea9de2b315
- Release Artefact: meta-mingw-a4ba674d6a0a17e4c0bc4c11bbb9d0ea9de2b315
- sha: cea731150cd3caedd90ca6a82bf050a00c3705cea166d24a6077d07b1b7b2404
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0/meta-mingw-a4ba674d6a0a17e4c0bc4c11bbb9d0ea9de2b315.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0/meta-mingw-a4ba674d6a0a17e4c0bc4c11bbb9d0ea9de2b315.tar.bz2>

bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.18
- Tag: yocto-6.0
- Git Revision: 33581c84f3a85008239acbd940501a35de48dc91
- Release Artefact: bitbake-33581c84f3a85008239acbd940501a35de48dc91
- sha: 8a0b0243b50b6e004f3350824628f69ee66be0d3a28bc25f3d96b35406015ba7
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0/bitbake-33581c84f3a85008239acbd940501a35de48dc91.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0/bitbake-33581c84f3a85008239acbd940501a35de48dc91.tar.bz2>

### 17.3.2 Migration notes for 6.0 (wrynose)

This section provides migration information for moving to the Yocto Project 6.0 Release (codename "wrynose") from the prior release. For a list of new features and enhancements, see the *Release notes for 6.0 (wrynose)* section.

The 6.0 (wrynose) release is the new LTS release after 5.0 (scarthgap). If you are migrating from the 5.0 version, be sure to read the previous migration guides:

- *Release 5.1 (styhead)*
- *Release 5.2 (walnascar)*
- *Release 5.3 (whinlatter)*

See also the list of new features and enhancements of the previous releases:

- *Release notes for 5.1 (styhead)*
- *Release notes for 5.2 (walnascar)*
- *Release notes for 5.3 (whinlatter)*

### Supported kernel versions

The `OLDEST_KERNEL` setting is 5.15 in this release, meaning that out the box, older kernels are not supported. See *4.3 migration notes* for details.

## Supported distributions

Compared to the previous releases, running BitBake is supported on new GNU/Linux distributions:

- Fedora 43
- openSUSE Leap 16.0
- Ubuntu 26.04 (LTS)

On the other hand, some earlier distributions are no longer supported:

- Fedora 39
- Fedora 40
- Fedora 41
- openSUSE Leap 15.5

See *all supported distributions*.

## BitBake fetcher removals

The following *BitBake* fetchers have been disabled or removed:

- The `npm` and `npmw` (**NPM**) fetchers were disabled due to security concerns (355cd22) and lack of maintenance.

All associated tests have been disabled.

- Support for the `Bazaar` fetcher was dropped (8e057d5).
- Support for the `OSC` fetcher was dropped (99497c1).
- Support for the `CVS` fetcher was dropped (5427500).

## Default `INIT_MANAGER` definition changed to `systemd`

The default definition of `INIT_MANAGER` in the `defaultsetup.conf` file was changed from `none` to `systemd`.

This means that users of the default distro setup (appearing as the `nodistro` *DISTRO*) will be using `systemd` as the default init manager.

This does not change the default init manager of the *Poky* distribution, which remains `SysVinit`.

Reverting to `SysVinit` can be done by specifying the `INIT_MANAGER` in your own *DISTRO* configuration file:

```
INIT_MANAGER = "sysvinit"
```

See commit 0b4061c for more information.

## Changes in how default `DISTRO_FEATURES` and `MACHINE_FEATURES` are provided

The way default `DISTRO_FEATURES` and `MACHINE_FEATURES` are provided by the *OpenEmbedded Build System* has changed.

The `DISTRO_FEATURES_BACKFILL`, `DISTRO_FEATURES_BACKFILL_CONSIDERED`, `DISTRO_FEATURES_DEFAULT`, `MACHINE_FEATURES_BACKFILL` and `MACHINE_FEATURES_BACKFILL_CONSIDERED` variables are now obsolete.

Instead, these are replaced by the `DISTRO_FEATURES_DEFAULTS`, `DISTRO_FEATURES_OPTED_OUT`, `MACHINE_FEATURES_DEFAULTS` and `MACHINE_FEATURES_OPTED_OUT` variables.

Users are advised to migrate to these variables the following way:

- For `DISTRO_FEATURES`:
  - If you have previously assigned `DISTRO_FEATURES` without using `DISTRO_FEATURES_DEFAULT`, you will now get the default features added automatically (from `DISTRO_FEATURES_DEFAULTS`). You will need to review these and add any features you do not want to use to `DISTRO_FEATURES_OPTED_OUT`.
  - `DISTRO_FEATURES_DEFAULT` is now unused, the new variable name is slightly different (`DISTRO_FEATURES_DEFAULTS`) to ensure that it is not accidentally used if a layer hasn't been modified to adapt to the new naming.
  - If you previously set `DISTRO_FEATURES_BACKFILL_CONSIDERED`, use the new `DISTRO_FEATURES_OPTED_OUT` variable instead.
  - If you previously modified `DISTRO_FEATURES_BACKFILL`, remove these assignments and follow the above instructions.
- For `MACHINE_FEATURES`:
  - `MACHINE_FEATURES` will now get the default features added automatically (from `MACHINE_FEATURES_DEFAULTS`). You will need to review these and add any features you do not want to use to `MACHINE_FEATURES_OPTED_OUT`.
  - If you previously set `MACHINE_FEATURES_BACKFILL_CONSIDERED`, use the new `MACHINE_FEATURES_OPTED_OUT` variable instead.
  - If you previously modified `MACHINE_FEATURES_BACKFILL`, remove these assignments and follow the above instructions.

See commit [159148f](#) and [3194d68](#) for more information.

### Changes to the list of `DISTRO_FEATURES` enabled by default

The following `DISTRO_FEATURES` are now enabled by default in `meta/conf/bitbake.conf`:

- `multiarch`: Enable building applications with multiple architecture support.
- `opengl`: Include the Open Graphics Library, which is a cross-language multi-platform application programming interface used for rendering two and three-dimensional graphics.
- `ptest`: Enable building the package tests where supported by individual recipes. To add the built `ptest` packages to the image, add `ptest-pkgs` to `IMAGE_FEATURES` in your image recipe.
- `vulkan`: Include support for the Vulkan API.
- `wayland`: Include the Wayland display server protocol and the library that supports it.

See commit [2e1e7c8](#) for more information.

## Default configuration templates removed from meta-poky

The configuration templates located in `meta-poky/conf/templates/default` have been removed as they are now provided in a single location: *OpenEmbedded-Core (OE-Core)* `meta/conf/templates/default`.

See commit [ac300ba](#) for more information on the differences between the two sets of default templates.

## native and cross classes `DEBUG_BUILD` change

Previously, setting `DEBUG_BUILD` to "1" globally would prevent the *OpenEmbedded Build System* from stripping target, *native* and *cross* binaries. This was changed so that only **target** binaries are stripped when this variable is set.

This change can be reverted by setting the two following lines in a *configuration file*:

```
INHIBIT_SYSROOT_STRIP:class-cross = "${@oe.utils.vartrue('DEBUG_BUILD', '1', '', '↵
↵d) }"
INHIBIT_SYSROOT_STRIP:class-native = "${@oe.utils.vartrue('DEBUG_BUILD', '1', '', '↵
↵d) }"
```

See commit [3c29afe](#) for more information.

## U-Boot configuration flow changes (*uboot-config*)

Declaring multiple U-Boot configurations used to be entirely defined by one `UBOOT_CONFIG` variable flag per configuration, e.g.:

```
UBOOT_CONFIG ??= "foo bar"
UBOOT_CONFIG[foo] = "config,images,binary"
UBOOT_CONFIG[bar] = "config2,images2,binary2"
```

This has now been split into more variable flags, e.g.:

```
UBOOT_CONFIG ??= "foo bar"
UBOOT_CONFIG[foo] = "config"
UBOOT_CONFIG[bar] = "config2"

UBOOT_CONFIG_IMAGE_FSTYPES[bar] = "fstype"

UBOOT_CONFIG_BINARY[foo] = "binary"

UBOOT_CONFIG_MAKE_OPTS[foo] = "FOO=1"
UBOOT_CONFIG_MAKE_OPTS[bar] = "BAR=1"

UBOOT_CONFIG_FRAGMENTS[foo] = "foo.fragment"
```

See the documentation of the *uboot-config* for full details.

While the previous legacy approach is still supported, it will be removed in for the next release. Users are advised to migrate to the new approach.

See commit [cd9e730](#) for more information.

#### Nota

Single configuration builds have not changed and are still declared using the following statements:

```
UBOOT_MACHINE = "config"
UBOOT_BINARY = "u-boot.bin"
```

### ***pkgconfig*-related variables are no longer automatically exported**

All the *pkgconfig*-related variables, such as *PKG\_CONFIG\_PATH*, are no longer exported in *meta/conf/bitbake.conf* with the *export* directive.

These *export* statements have been moved to the *pkgconfig* class, meaning recipes using these variables that not yet inheriting the *pkgconfig* class should now inherit it with:

```
inherit pkgconfig
```

See commit [68d2d38](#) for more information.

### ***vex* output JSON document extension change**

Image recipes that inherit the *vex* class have an extra JSON document generated which was previously ending with the *.json* suffix. For example, a build for the *core-image-minimal* image recipe with this class inherited would have resulted in a file named:

```
core-image-minimal-qemuarm64.rootfs.json
```

The suffix of this file is now *.vex.json*. Taking the above example, the same file is now named:

```
core-image-minimal-qemuarm64.rootfs.vex.json
```

### **Support for SPDX 2.2 removed**

Support for generating SPDX 2.2 document through the *create-spx-2.2* class was removed:

```
Removes SPDX 2.2 support in favor of SPDX 3 support being the only
option. The SPDX 3 data is far superior to SPDX 2.2 and thus more useful
for SBOM uses cases.
```

See commit [12abd05](#) for more information.

Users are advised to transition to SDPX 3.0, which is provided by the *create-spx* class.

**cve-check class removed**

The `cve-check` class was removed and replaced by the *sbom-cve-check* class. Quoting the commit removing the class (00de455):

It's been long known that the `cve-check` class in `oe-core` is not that usable in the real world, for more details see "Future of CVE scanning in Yocto"[1]. This mail proposed an alternative direction that included a CVE scanning tool that can be ran both during the build and afterwards, so that periodic scans of a previously build image is possible.

Last year, Bootlin wrote `sbom-cve-check`[2] and I compared this to my proposal in "Comparing `cve-check` with `sbom-cve-check`"[3], concluding that this is likely the missing piece.

Support for `sbom-cve-check` has been merged into `oe-core`, and the `cve-check` class is now obsolete. So that we don't have to maintain it for the four-year lifecycle of the Wrynose release, delete it.

This patch also deletes the database fetcher recipes, and the test cases that were specific to `cve-check`. Note that the `oe.cve_check` library still exists as this is used by the SPDX classes.

[1] <https://lore.kernel.org/openembedded-core/7D6E419E-A7AE-4324-966C-3552C586E452@arm.com/>  
 [2] <https://github.com/bootlin/sbom-cve-check>  
 [3] <https://lore.kernel.org/openembedded-core/2CD10DD9-FB2A-4B10-B98A-85918EB6B4B7@arm.com/>

Users currently using the `cve-check` class are advised to switch to *sbom-cve-check*:

- The following assignment:

```
INHERIT += "cve-check"
```

Should be removed and replaced by:

```
OE_FRAGMENTS += "core/yocto/sbom-cve-check"
```

This will enable the *sbom-cve-check* class along with the recommended settings.

This will deploy two files to the deployment directory (*DEPLOY\_DIR\_IMAGE*) after building an image:

- A file ending with `.sbom-cve-check.yocto.json`: this is the output JSON report in the same format as the one deployed by the `cve-check` class.
- A file ending with `.sbom-cve-check.spdx.json`: this is an output SPDX report annotated with vulnerable CVEs.

- The `cve-check` class output summary file (deployed in the `DEPLOY_DIR_IMAGE`) ending with `.cve.txt` is no longer deployed by default but can be brought back by adding the following statement to a configuration file:

```
SBOM_CVE_CHECK_EXPORT_VARS:append = " SBOM_CVE_CHECK_EXPORT_SUMMARY"
```

This will deploy a new file ending with `.cve.txt`, which uses the same format as the summary previously deployed by the `cve-check` class.

See the documentation of `SBOM_CVE_CHECK_EXPORT_VARS` for more details.

- The `CVE_CHECK_SHOW_WARNINGS` variable, which was used to control whether the `cve-check` would print warning when unpatched CVEs were found, is now removed and replaced by the `SBOM_CVE_CHECK_SHOW_WARNINGS` variable, which does the same.

See the *Verifica delle Vulnerabilità* section of the Yocto Project Security Manual for more information.

### **`CVE_PRODUCT` character escaping change**

The `CVE_PRODUCT` variable, which specifies a name used to match the recipe name against the name in the upstream NIST CVE database, used to require special characters to be escaped.

This is no longer the case. For example, the `CVE_PRODUCT` variable for the `webkitgtk` recipe must no longer be written as `webkitgtk\+` but `webkitgtk+`.

Users are advised to review their `CVE_PRODUCT` assignments and remove any special character escaping.

### **`WIC_SECTOR_SIZE` should be replaced by `--sector-size`**

The `WIC_SECTOR_SIZE` variable was previously used to define the sector size of the partitions generated by the `WIC` tool. The `wic` command-line tool now supports a `--sector-size` argument that replaces this variable.

While this variable can still be used in recipes, a warning is now printed on the console when used:

```
DEPRECATED: WIC_SECTOR_SIZE is deprecated, use the --sector-size command-line_
↔argument instead.
```

Using the `--sector-size` command-line argument can be done through the `WIC_CREATE_EXTRA_ARGS` variable.

For example, a previous assignment to `WIC_SECTOR_SIZE`:

```
WIC_SECTOR_SIZE = "4096"
```

Should be replaced by:

```
WIC_CREATE_EXTRA_ARGS += "--sector-size 4096"
```

See commit [b50d6de](#) for more information.



### WIC kickstart files to be moved under `files/wic`

WIC kickstart files (*WKS* files) should be moved to the `files/wic/` directory of the layer containing them.

If not done, the build will fail with errors indicating how to move these files, for example:

```
wic/wks files at ../meta-custom/wic need to be moved to files/wic within the layer.
↳to be found/used
wic/wks files at ../meta-custom/scripts/lib/wic/canned-wks need to be moved to
↳files/wic within the layer to be found/used
```

For example, here is the content of the *OpenEmbedded-Core (OE-Core)* "meta" layer as of writing:

```
meta/files/wic
├─ common.wks.inc
├─ directdisk-bootloader-config.cfg
├─ directdisk-bootloader-config.wks
├─ directdisk-gpt.wks
├─ directdisk-multi-rootfs.wks
├─ directdisk.wks
├─ efi-bootdisk.wks.in
├─ efi-uki-bootdisk.wks.in
├─ mkefidisk.wks
├─ mkhybridiso.wks
├─ qemuloongarch.wks
├─ qemuriscv.wks
├─ qemux86-directdisk.wks
├─ sdimage-bootpart.wks
└─ systemd-bootdisk.wks
```

This change does not affect *WIC plugins*, which should remain in `scripts/lib/wic/plugins/source/`.

### Support for SysVinit compatibility in systemd was dropped

Support for the *SysVinit* compatibility in *systemd* was dropped.

This is due to *recent announcements* in *systemd* which is planning to drop support for the *SysVinit* compatibility.

This means that the *systemd* and *sysvinit* *distro features* cannot be used together anymore.

Users are advised to switch to one init manager or the other entirely.

See commit [d9ec9e2](#) for more information.

### Removed recipes

The following recipes have been removed in this release:

- *jquery*: The last users of this recipe were the reproducible tests, but have been reworked to use the *jQuery* CDN instead with [d3ee549](#) (See [aae793a](#))
- *systemd-compat-units*: Dropped as a consequence of removing *SysVinit* support in *systemd* ([d9ec9e2](#))

- gstreamer1.0-vaapi: removed as it was already provided by the `va` [PACKAGECONFIG](#) item of `gstreamer1.0-plugins-bad`. ([9e2d2a5](#))
- pkgconfig: replaced by the `pkgconf` recipe ([e32bf38](#))
- python3-pyzstd: there were no users of this in *OpenEmbedded-Core (OE-Core)* and Python 3.14 now has built-in support for `zstd` ([55061de](#))
- cve-update-db-native, cve-update-nvd2-native: removed with the `cve-check` class removal as it was the only user of these recipes. ([00de455](#))
- python3-roman-numerals-py: renamed to `python3-roman-numerals` ([faff756](#))

### Removed [PACKAGECONFIG](#) options

- mesa: freedreno-fdperf ([293edd0](#))
- libcxx: no-atomics ([ccc585f](#))
- systemd: sysvinit ([e00d5d6](#))
- gstreamer1.0-plugins-good: soup2 ([61d6535](#))
- webkitgtk: soup2 ([69af433](#))

### Removed classes

The following classes have been removed in this release:

- oelint: remove as most of the checks done by this class are done in other areas of code now, making this class obsolete.

### Miscellaneous changes

- [meson](#): drop `meson_do_qa_configure` as it was non-functional ([0514b45](#))
- Drop VSCode setup support from the `oe-init-build-env` script. Users are advised to use [bitbake-setup](#) instead ([4e781c6](#))

## 17.3.3 Release notes for Yocto-6.0.1 (Wrynose)

### Security Fixes in Yocto-6.0.1

- avahi: Fix [CVE-2026-34933](#)
- base-files: Ignore [CVE-2018-6557](#)
- bind: Ignore [CVE-2017-3139](#)
- busybox: fix [CVE-2024-58251](#) and [CVE-2026-29004](#)
- cargo: Ignore [CVE-2023-40030](#)
- cve-extra-exclusions: Ignore [CVE-2019-2708](#)
- ffmpeg: Ignore [CVE-2022-2566](#), [CVE-2025-9951](#), [CVE-2025-59729](#) and [CVE-2025-59730](#)

- git: Ignore CVE-2024-32002, CVE-2024-50349, CVE-2024-52006, CVE-2025-48385 and CVE-2025-48386
- glibc: Fix CVE-2026-4046
- gnutls: Ignore CVE-2026-1584
- harfbuzz: Ignore CVE-2024-56732
- inetutils: Fix CVE-2026-32772
- libarchive: Ignore CVE-2026-4426 and CVE-2026-5745
- libsoup: Fix CVE-2026-2708 and CVE-2026-5119
- libsoup: Ignore CVE-2026-2369 and CVE-2026-2436
- libssh2: Fix CVE-2026-7598
- libva: Ignore CVE-2023-39929
- ovmf: Ignore CVE-2024-38796, CVE-2024-38797, CVE-2024-38798, CVE-2024-38805, CVE-2025-2295, CVE-2025-2296 and CVE-2025-3770
- p11-kit: Ignore CVE-2026-2100
- python3-requests: Ignore CVE-2024-35195 and CVE-2024-47081
- python3-setuptools: Ignore CVE-2024-6345
- rsync: Ignore CVE-2024-12084
- ruby: Ignore CVE-2025-0306
- sed: Fix CVE-2026-5958
- sudo: Fix CVE-2026-35535
- tiff: Fix CVE-2026-4775

## Fixes in Yocto-6.0.1

### bitbake

- README: Add "2.18" subject-prefix to git-send-email suggestion
- b4-config: add send-prefixes for 2.18/wrynose
- fetch/git: Fix leaking of temporary directory
- fetch/git: Improve temporary directory handling
- fetch/wget: in upstream version checks, match versioned directories exactly
- fetch2/crate: use CDN endpoint for version checking if possible
- fetch2/crate: use CDN for fetching crates

## meta-yocto

- poky.conf: Bump version for 6.0.1 release

## openembedded-core

- README: Add wrynose subject-prefix to git-send-email suggestion
- apr-util: Add *CVE\_PRODUCT* to support product name
- apr: Add *CVE\_PRODUCT* to support product name
- b4-config: add send-prefixes for wrynose
- bluez5: add patches to fix 8.56 cli & gatt issues
- build-appliance-image: Update to wrynose head revisions
- build-appliance-image: fix branches for wrynose revisions
- cargo: set *CVE\_PRODUCT*
- ccache: upgrade to 4.13.3
- classes/base: add explicit bzip2-native dependency for unpacking .bz2
- coreutils: set *CVE\_PRODUCT*
- default-distrovars.inc: add missing spaces in append overrides
- devtool: Disable gpg signing when setting up source tree repos
- dhcpcd: upgrade to 10.3.1
- efivar: Backport patch to fix -march issue for ppc64le
- features-check.bbclass: add reference to required *TUNE\_FEATURES*
- glibc: Fix recipe bug that disabled stack protector
- glibc: stable 2.43 branch updates
- groff: upgrade to 1.24.1
- gsettings-desktop-schemas: upgrade to 50.1
- gtk4: upgrade to 4.22.2
- gtk+3: upgrade to 3.24.52
- hwdata: upgrade to 0.406
- mirrors: remove inactive sources.openembedded.org URLs
- oe-pkgdata-util: fix empty runtime-rprovides directory handling
- oe-pkgdata-util: fix runtime-rprovides handling in lookup\_pkg error path
- package.py: fix kernel module file pre-filter and document strip asymmetry
- perf: add *PACKAGECONFIG* for llvm
- pseudo: Upgrade to 1.9.7

- python3-requests: Increase chardet upper limit
- python3-sbom-cve-check: Update to version 1.3.1
- qemu: fix iotlb\_to\_section() for different AddressSpace
- rust: fix codegen test failure on big-endian targets
- sbom-cve-check-update-cvelist-native: Update source revision
- sbom-cve-check-update-nvd-native: Update source revision
- sbom-cve-check: set *PV* from upstream tags and ensure version checks are correct
- scripts/makefile-getvar: quote MAKEFILE variable
- sed: upgrade to 4.10
- shadow-native: Change upstream status of disable\_syslog.patch
- shadow: set *CVE\_PRODUCT*
- sudo: set *CVE\_PRODUCT*
- tzdata/tzcode-native: upgrade to 2026b
- utils: Handle unexpanded variables in *DISTRO\_FEATURES*
- wireless-regdb: upgrade to 2026.03.18

## yocto-docs

- "Transitioning ..." doc: Various pedantic cleanups
- Quick Build guide: Various pedantic cleanups
- What I Wish I'd KNown: Various pedantic cleanups
- YP Quick Build: delete extraneous periods in list
- YP Quick Build: use "set up" as a verb
- conf.py: add a :yocto\_bug: role
- contributor-guide: fix type "maintainance" to "maintenance"
- dev-manual: "--runonly" should be "--runall"
- docs-wide: drop documentation for cve-check and variables
- index.rst: update "Software Overview" to "Technical Overview"
- migration-guide: add release notes for 4.0.35 5.3.4
- migration-guide: migration-6.0: fix typos in cve-check removal
- migration-guides/migration-6.0.rst: add migration notes on cve-check removal
- migration-guides/migration-6.0.rst: document the *CVE\_PRODUCT* behavior change
- migration-guides/migration-6.0.rst: mention python3-roman-numerals-py rename

- migration-guides/release-notes-6.0.rst: add contributors, CVE fixes, downloads, known issue, license, recipe version changes
- migration-guides: fix <https://> prefix missing in anonymous reference
- migration-guides: migration-6.0: fix grammar and missing word
- migration-guides: migration-6.0: reword meta-poky templates removal
- migration-guides: release-notes-6.0: fix typo in documentation changes
- overview-manual/concepts.rst: fix do\_prepare\_recipe\_sysroot task description
- overview-manual: fix "checkout" versus "check out"
- ref-manual/system-requirements.rst: add CentOS 10 as a supported distro
- ref-manual/variables.rst: document the `SBOM_CVE_CHECK_SHOW_WARNINGS` variable
- ref-manual/variables: IMAGE\_TYPES: add new wicenv type
- ref-manual/variables: document the 'dynamic layer' concept
- ref-manual: classes: add missing "task" after create\_recipe\_sbom
- ref-manual: classes: fix <https://> prefix missing in anonymous reference
- ref-manual: fix "include to" grammar for `UKI_DEVICETREE`
- ref-manual: fragments: fix style inconsistencies
- ref-manual: replace "naive" with "simple"
- ref-manual: variables: add hyphen to "space separated" and "auto generated"
- security-manual/vulnerabilities.rst: refresh the document after cve-check removal
- security-manual/vulnerabilities.rst: require Upstream-Status, not recommend
- tools/build-docs-container: add CentOS 10 support
- tools/build-docs-container: add missing leap 16.0 in help message
- yp-intro.rst: add link to "buildbot"
- yp-intro.rst: delete really old references

### Known Issues in Yocto-6.0.1

- N/A

### Contributors to Yocto-6.0.1

Thanks to the following people who contributed to this release:

- Alexander Kanavin
- Andrew Geissler
- Ankur Tyagi
- Antonin Godard

- Benjamin Robin (Schneider Electric)
- Chen Qi
- Daniel McGregor
- Dawid Bijak
- Dmitry Sakhonchik
- Himanshu Jadon
- Ivan Nestlerode
- Jinwang Li
- Johan Anderholm
- João Marcos Costa
- Lee Chee Yang
- Leonardo Costa
- Li Wang
- Minwoo Choi
- Moritz Haase
- Paul Barker
- Peter Marko
- Peter Tatrai
- Quan Sun
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Ross Burton
- Sam Kent
- Thomas Perrot
- Vijay Anusuri
- Wang Mingyu
- Yoann Congal

### Repositories / Downloads for Yocto-6.0.1

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [wrynose](#)

- Tag: `yocto-6.0.1`
- Git Revision: `7ac955621b36a221126cd40f12c41fa98c213a24`
- Release Artefact: `yocto-docs-7ac955621b36a221126cd40f12c41fa98c213a24`
- sha: `32e25828d25662db5e92829ae6a471291e27d950b5c273458fae211a776e4131`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.1/yocto-docs-7ac955621b36a221126cd40f12c41fa98c213a24.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.1/yocto-docs-7ac955621b36a221126cd40f12c41fa98c213a24.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `wrynose`
- Tag: `yocto-6.0.1`
- Git Revision: `06dd66e6220e5ce4ed4b9af4d8231ae5f0a8ce80`
- Release Artefact: `oecore-06dd66e6220e5ce4ed4b9af4d8231ae5f0a8ce80`
- sha: `26de701c73d43ab8904bc57b162385901f9a1114807b3e28b665437d4ba23624`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.1/oecore-06dd66e6220e5ce4ed4b9af4d8231ae5f0a8ce80.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.1/oecore-06dd66e6220e5ce4ed4b9af4d8231ae5f0a8ce80.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `wrynose`
- Tag: `yocto-6.0.1`
- Git Revision: `8251bdad5fda780a000fb41e6eda82eadf0fa39e`
- Release Artefact: `meta-yocto-8251bdad5fda780a000fb41e6eda82eadf0fa39e`
- sha: `ac9125ddd150febba0da9ae4fb7e222dde1d6e8f2ad3aaae1c0c2a4c1f738f36`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.1/meta-yocto-8251bdad5fda780a000fb41e6eda82eadf0fa39e.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.1/meta-yocto-8251bdad5fda780a000fb41e6eda82eadf0fa39e.tar.bz2>

#### bitbake



- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.18
- Tag: yocto-6.0.1
- Git Revision: 22021758e66737bcf68dfd2b74adc6a0cb1d42d9
- Release Artefact: bitbake-22021758e66737bcf68dfd2b74adc6a0cb1d42d9
- sha: ce9c213f9b8c5fb677b0a64ac883386a4d578fdb66881dcc9f1cd8bc4e79e7f6
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.1/bitbake-22021758e66737bcf68dfd2b74adc6a0cb1d42d9.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.1/bitbake-22021758e66737bcf68dfd2b74adc6a0cb1d42d9.tar.bz2>

### 17.3.4 Release notes for Yocto-6.0.2 (Wrynose)

This release removed the linux-yocto 6.18 CVE exclusion list (`meta/recipes-kernel/linux/cve-exclusion_6.18.inc`) as sbom-cve-check now natively handles CVE status.

#### Security Fixes in Yocto-6.0.2

- bind: Fix CVE-2026-3039, CVE-2026-3592, CVE-2026-3593, CVE-2026-5946, CVE-2026-5947 and CVE-2026-5950
- cups: Fix CVE-2026-34978, CVE-2026-34979, CVE-2026-34980, CVE-2026-34990, CVE-2026-39314 and CVE-2026-39316
- curl: Fix CVE-2026-6276
- go: Fix CVE-2026-27145, CVE-2026-33811, CVE-2026-33814, CVE-2026-39817, CVE-2026-39819, CVE-2026-39820, CVE-2026-39823, CVE-2026-39825, CVE-2026-39826, CVE-2026-39836, CVE-2026-42499, CVE-2026-42501, CVE-2026-42504 and CVE-2026-42507
- libinput: Fix CVE-2026-50292
- libsolv: Fix CVE-2026-9150
- libusb1: Fix CVE-2026-23679 and CVE-2026-47104
- openssl: Fix CVE-2026-7383, CVE-2026-9076, CVE-2026-34180, CVE-2026-34181, CVE-2026-34182, CVE-2026-34183, CVE-2026-42764, CVE-2026-42766, CVE-2026-42767, CVE-2026-42768, CVE-2026-42769, CVE-2026-42770, CVE-2026-45445, CVE-2026-45446 and CVE-2026-45447
- python3: Fix CVE-2026-1502, CVE-2026-3087, CVE-2026-3298, CVE-2026-4786, CVE-2026-5713, CVE-2026-6019 and CVE-2026-6100
- qemu: Fix CVE-2024-6519
- xserver-xorg: Fix CVE-2026-33999, CVE-2026-34000, CVE-2026-34001, CVE-2026-34002 and CVE-2026-34003

- xwayland: Fix [CVE-2026-33999](#), [CVE-2026-34000](#), [CVE-2026-34001](#), [CVE-2026-34002](#) and [CVE-2026-34003](#)

## Fixes in Yocto-6.0.2

### bitbake

- bitbake: fix issue with varflag exclusion
- fetch2/crate: guard against empty version list
- fetch2/crate: skip yanked versions when reading cargo index
- fetch2/git: quote shallow extra ref arguments
- fetch2/wget: limit auth on checkstatus redirects
- fetch2: Unpack RPMs with --no-absolute-filenames
- fetch2: allow empty value for params while formatting URI string.
- fetch2: reraise IOError during download
- fetch2: validate deb/ipk data member names
- fetch2: validate striplevel parameter
- hashserv/tests: use valid 64-character unihashes
- hashserv: validate unihash values
- layerindexlib: restapi.py: fix unbound variable
- tests/fetch: cover checkstatus redirect auth handling
- toaster: use https for clones, remove cgit in links in defaults

### meta-yocto

- poky.conf: Bump version for 6.0.2 release

### openembedded-core

- bind: upgrade to 9.20.23
- binutils: Upgrade to 2.46.1
- build-appliance-image: Update to wrynose head revisions
- ca-certificates: upgrade to 20260601
- classes/gtk-icon-cache: fix libdir passed to the postrm intercept
- conf/machine: fix typos in ARM and x86 README files
- curl: fix mbedtls detection
- dropbear: Clarify [LICENSE](#) and drop PD
- gcc: Upgrade GCC to 15.3 release

- gettext-minimal-native: Use SPDX License Identifier
- glib-2.0-native: Remove problematic path reference
- glib-2.0: Change from Public Domain to Gnome GCR Documentation License
- go: upgrade to 1.26.4
- gstreamer1.0-plugins-bad: handle padded buffers in wl\_shm buffer creation
- libpcap: fix error message on 32-bit integer overflow
- libstdl2: Fix compilation error with DirectFB
- licenses: Update with the pull-sdpx-licenses.py script to 3.28.0
- linux-yocto: remove CVE exclusion list, sbom-cve-check does this itself
- lttnng-modules: Fix trace\_hrtimer\_start build failure
- matchbox-panel-2: backport patch to set a constant size for the clock
- mobile-broadband-provider-info: Fix license to be CC-PDDC
- net-tools: Handle binmerge
- oeqa/core/runner: stub addDuration in OETestResult
- openssl: upgrade to 3.5.7
- perf: disable BUILD\_BPF\_SKEL by default
- perf: make libraries for install\_headers configurable
- pixman: Change PD license to HPND-sell-variant
- ppp: Remove PD license
- pseudo: Update to version 1.9.8
- python3-pycryptodome: Update *LICENSE* PD -> Unlicense
- python3-pyelftools: Update license to Unlicense
- python3: Fix ThreadingMock call\_count race condition
- python3: sanitize userbase in \_sysconfig\_vars JSON to avoid host path leak
- python3: upgrade to 3.14.5
- python3targetconfig: pull in nativesdk python when building nativesdk recipes
- rust: export CARGO\_BUILD\_TARGET
- sbom-cve-check-common: Fatalize command failure
- sbom-cve-check: Fix breakage with empty *IMAGE\_LINK\_NAME*
- scripts/install-buildtools: Update to 6.0.1
- sqlite3: Use SPDX identifier
- squashfs-tools: add another CPE

- sstate: Detect broken sstate paths containing tmpdir
- udev-extraconf: use -H for unmount tmpfile find
- util-macros: Remove redundant MIT license
- wireless-regdb: upgrade to 2026.05.30
- xserver-xorg/xwayland: 'Clarify' xserver license
- xserver-xorg/xwayland: Drop X11-swapped from [LICENSE](#)
- xserver-xorg: upgrade to 21.1.22
- xwayland: upgrade 24.1.9 -> 24.1.11

### yocto-docs

- Document shared state signing
- bsp-guide: mention bootloader and device tree in BSP intro
- bsp-guide: simplify example of structure of BSP layer
- bsp-guide: update guide to reflect newer beaglebone
- build-manual: update [ROOTFS\\_POSTPROCESS\\_COMMAND](#) example
- contributor-guide: couple minor typo/grammar fixes
- dev-manual: SysVinit is the default init manager for Poky
- dev-manual: change "setup" to "set up" when used as an action
- dev-manual: drop "PREFERRED\_VERSION" from x86-base.inc snippet
- dev-manual: fix broken grammar in "Libraries" section
- dev-manual: fix grammatical error, missing word "with"
- dev-manual: fully define SOLIBS-related variables in bitbake.conf
- dev-manual: remove semicolons for rootfs commands
- dev-manual: update [AUTOREV](#) explanation to match current file
- kernel-dev: remove references to defunct LTSI project
- migration-guide: Fix migration scripts
- migration-guide: add release notes for 5.0.18
- overview-manual/concepts: convert several .png to SVG
- overview-manual/svg: remove white backgrounds
- overview-manual: add ":term:" for OE Build System
- overview-manual: correct that "conf" is a subdir of build dir
- overview-manual: explain "ODM" and "OSV" acronyms
- overview-manual: fix typo, "semi-colon" -> "colon"

- overview-manual: hyphens not allowed in file version
- overview-manual: inform the reader early of "bitbake-getvar"
- overview-manual: mention that patch files can be compressed
- overview-manual: provide a more expansive definition of "layer"
- overview-manual: remind reader that meta-poky is a distro layer
- overview-manual: update deploy.bbclass snippet
- overview-manual: use correct spelling "counterpart"
- recipe-style-guide.rst: two minor grammatical tweaks
- ref-manual/variables.rst: link \*MIRRORS definitions to the BitBake manual
- ref-manual: add more explanation to glossary variable *LICENSE*
- ref-manual: clarify that *PACKAGE\_EXCLUDE* supports DEB packaging
- ref-manual: clarify use of "PACKAGE\_ARCH" in a packagegroup
- ref-manual: document *RM\_WORK\_EXCLUDE\_ITEMS* variable
- ref-manual: update glossary entries for packaging backend variables
- security-manual: some grammar and wording fixes in intro
- security-team.rst: update my email address and key
- security-team: Add section on multi-project embargoes
- security-team: Tidy and update section on security team operations
- security-team: Update membership list

### Known Issues in Yocto-6.0.2

- N/A

### Contributors to Yocto-6.0.2

Thanks to the following people who contributed to this release:

- Abhishek Bachiphale
- Adarsh Jagadish Kamini
- Alexander Kanavin
- Anders Heimer
- Anil Dongare
- Ankur Tyagi
- Anthony Squires
- Antonin Godard
- Bin Cao

- David Reyna
- Deepak Rathore
- Harish Sadineni
- He Zhe
- Hemanth Kumar M D
- Jate Sujjavanich
- Jesse Van Gavere
- Jinfeng Wang
- Joshua Watt
- João Marcos Costa
- Jörg Sommer
- Lee Chee Yang
- Marcio Henriques
- Mark Hatle
- Mark Jonas
- Marta Rybczynska
- Niko Mauno
- Omkar Patil
- Paul Barker
- Peter Marko
- Prabhudasu Vatala
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Ross Burton
- Sai Sneha
- Thomas Perrot
- Tushar Darote
- Vyacheslav Yurkov
- Wang Mingyu
- Yoann Congal
- hongxu

## Repositories / Downloads for Yocto-6.0.2

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `whinlatter`
- Tag: `yocto-6.0.2`
- Git Revision: `2c59a23fc39d92831cb55a0e5f713d20f94730d4`
- Release Artefact: `yocto-docs-2c59a23fc39d92831cb55a0e5f713d20f94730d4`
- sha: `ed297179a81884c892ca4fac44be163e9603c77d2ca84462b7b29a772c427236`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.2/yocto-docs-2c59a23fc39d92831cb55a0e5f713d20f94730d4.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.2/yocto-docs-2c59a23fc39d92831cb55a0e5f713d20f94730d4.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `whinlatter`
- Tag: `yocto-6.0.2`
- Git Revision: `5d1aa5c806c061a2994f4decb59016610f093213`
- Release Artefact: `oecore-5d1aa5c806c061a2994f4decb59016610f093213`
- sha: `d7c5b514ebba36558921bf30b2f404521a46bbe38805011afb1f43ec60925c31`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.2/oecore-5d1aa5c806c061a2994f4decb59016610f093213.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.2/oecore-5d1aa5c806c061a2994f4decb59016610f093213.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `whinlatter`
- Tag: `yocto-6.0.2`
- Git Revision: `24c24cef5d1523fefe43a3e3d34667b37ae551f3`
- Release Artefact: `meta-yocto-24c24cef5d1523fefe43a3e3d34667b37ae551f3`
- sha: `d81d38f935efaf7f744f9f3b0b47e0c551dc4aad09343792813acad60a11ef2`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.2/meta-yocto-24c24cef5d1523fefe43a3e3d34667b37ae551f3.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.2/meta-yocto-24c24cef5d1523fefe43a3e3d34667b37ae551f3.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.18
- Tag: yocto-6.0.2
- Git Revision: acfe02fa38b5da9e6a36c6cedcf91d4fcbebfbbd
- Release Artefact: bitbake-acfe02fa38b5da9e6a36c6cedcf91d4fcbebfbbd
- sha: 13c93db11c6648ceed179408244a07111b6d6fb911749d46d160103fdd375ec9
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.2/bitbake-acfe02fa38b5da9e6a36c6cedcf91d4fcbebfbbd.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.2/bitbake-acfe02fa38b5da9e6a36c6cedcf91d4fcbebfbbd.tar.bz2>

## 17.3.5 Release notes for Yocto-6.0.3 (Wrynose)

### Security Fixes in Yocto-6.0.3

- bind: Fix CVE-2026-11331, CVE-2026-11721, CVE-2026-13321, CVE-2026-10723, CVE-2026-12617 and CVE-2026-10822
- binutils: Fix CVE-2026-6846
- bzip2: Fix CVE-2026-42250
- cargo: Fix CVE-2026-5222 and CVE-2026-5223
- cups: Fix CVE-2026-27447 and CVE-2026-41079
- curl: Fix CVE-2026-5545, CVE-2026-5773, CVE-2026-6253, CVE-2026-6429 and CVE-2026-7168
- curl: Ignore CVE-2026-10536 if nghttp2 not enabled
- dhcpcd: Fix CVE-2026-56113, CVE-2026-56114, CVE-2026-56116 and CVE-2026-56117
- expat: Fix CVE-2026-41080, CVE-2026-45186, CVE-2026-56132, CVE-2026-56403, CVE-2026-56404, CVE-2026-56405, CVE-2026-56406, CVE-2026-56407, CVE-2026-56408, CVE-2026-56409, CVE-2026-56410 and CVE-2026-56411
- gawk: Fix CVE-2026-40467, CVE-2026-40468, CVE-2026-40469 and CVE-2026-40553
- glib-2.0: Fix CVE-2026-58010, CVE-2026-58011, CVE-2026-58012, CVE-2026-58013, CVE-2026-58014, CVE-2026-58015 and CVE-2026-58016



- gnupg: Fix CVE-2026-57062
- gnutls: Fix CVE-2026-3832, CVE-2026-3833, CVE-2026-42009 and CVE-2026-33846
- go: Fix CVE-2026-39822 and CVE-2026-42505
- gstreamer1.0: Ignore CVE-2026-5056
- gzip: Fix CVE-2026-41991 and CVE-2026-41992
- libcap: Fix CVE-2026-4878
- libgcrypt: Fix CVE-2026-41989 and CVE-2026-41990
- libpng: Fix CVE-2026-34757
- libpng: Ignore CVE-2026-40930
- libsolv: Fix CVE-2026-9149
- libssh2: Fix CVE-2025-15661, CVE-2026-55199 and CVE-2026-55200
- libxml2: Fix CVE-2026-11979
- libxpm: Fix CVE-2026-4367
- openssh: Fix CVE-2026-59995, CVE-2026-59996, CVE-2026-59997, CVE-2026-59999, CVE-2026-60000, CVE-2026-60001 and CVE-2026-60002
- openssh: Ignore CVE-2026-59998 if kerberos not enabled
- openssh: Ignore CVE-2026-3497
- perl: Fix CVE-2026-8376
- python3: Fix CVE-2026-3276, CVE-2026-7210, CVE-2026-7774, CVE-2026-8328, CVE-2026-9669, CVE-2026-11940 and CVE-2026-11972
- python3-setuptools: Fix CVE-2026-59890
- python3-urllib3: Fix CVE-2026-44431
- qemu: Fix CVE-2025-14876, CVE-2026-0665 and CVE-2026-2243
- socat: Fix CVE-2026-56123
- sqlite3: Fix CVE-2026-11822 and CVE-2026-11824
- tar: Fix CVE-2026-5704
- util-linux: Fix CVE-2026-13595 and CVE-2026-27456
- vim: Fix CVE-2026-41411, CVE-2026-42307, CVE-2026-43961, CVE-2026-44656, CVE-2026-45130, CVE-2026-46483, CVE-2026-47162, CVE-2026-47167, CVE-2026-52858, CVE-2026-52859, CVE-2026-52860, CVE-2026-55892 and CVE-2026-57452

## Fixes in Yocto-6.0.3

### bitbake

- bitbake-setup: always write newline at end of the README
- utils: Add NFS EEXIST/kdir failure workaround

### meta-yocto

- README: Add wrynose subject-prefix to git-send-email suggestion
- b4-config: add send-prefixes for wrynose
- poky.conf: Bump version for 6.0.3 release
- yocto-bsps: update to v6.18.39

### openembedded-core

- baremetal-helloworld: Fix override order
- bc: set *CVE\_PRODUCT*
- bind: upgrade to 9.20.26
- bluez5: Fix sending extra bytes with MGMT\_OP\_ADD\_EXT\_ADV\_DATA
- bluez5: fix gatt cache sync issue
- bluez5: fix set volume failure
- bluez5: set L2CAP IMTU for OBEX profile listeners
- build-appliance-image: Update to wrynose head revisions
- clang/llvm: Upgrade to 22.1.8
- cmake-native: prevent host libidn2 contamination
- common-licenses/PHP-3.0: Correct the license text
- cpan\_build: disable .packlist and html doc
- create-spdx-image-3.0: correct *SSTATE\_SKIP\_CREATION* key for do\_create\_image\_sbom\_spdx
- devtool: provide explicit error for missing "script" command
- dmidecode: fix x86-only tools being installed on ARM targets
- dropbear: Add missing WTFPL & Unlicense in *LICENSE* and *LIC\_FILES\_CHKSUM*
- flac: fix buildpaths with doxygen enabled
- flac: make documentation build deterministic
- gdb: Upgrade to 17.2
- glib-2.0: upgrade to 2.88.2
- go: upgrade to 1.26.5

- i2c-tools: add LGPL-2.1-or-later license for libi2c
- kernel-fit-image.bbclass: Do not include kernel property in DTBO config subnodes
- kernel-fit-image.bbclass: Fix operation with `KERNEL_DTBVENDORED = "1"`
- kernel-fit-image: Add `KERNEL_DTBVENDORED` support for `FIT_CONF_DEFAULT_DTB`
- libjitterentropy: fix license statement
- libxpm: upgrade to 3.5.19
- linux-yocto/6.18: drm/virtio: fix deadlock in display\_info\_cb by removing hotplug from dequeue worker
- linux-yocto/6.18: qat/intel configuration warning fixes
- linux-yocto/6.18: update to v6.18.39
- nospdx: also drop do\_create\_recipe\_sbom
- oe-selftest: fitimage: Add tests for `KERNEL_DTBVENDORED`
- oe-selftest: fitimage: Do not expect kernel property in DTBO config subnodes
- opensbi: don't override ELFFLAGS, silence ldflags QA for bare-metal ELF's
- ovmf: fix tpm `PACKAGECONFIG` to use TPM2\_ENABLE
- package.bbclass: hardcode emit\_pkgdata to run last
- ptest-packagelists.inc: disable glib-2.0 for RISC-V64
- python3: skiptest tracemalloc\_track\_race
- python3: upgrade to 3.14.6
- python3-certifi: set `CVE_PRODUCT`
- python3-cryptography: set `CVE_PRODUCT`
- python3-idna: set `CVE_PRODUCT`
- python3-pip: set `CVE_PRODUCT`
- python3-ply: set `CVE_PRODUCT`
- python3-pyasn1: set `CVE_PRODUCT`
- python3-pyopenssl: set `CVE_PRODUCT`
- python3-pyyaml: set `CVE_PRODUCT`
- python3-xmltodict: set `CVE_PRODUCT`
- qemu-boot.bbclass: add missing task dependency on kernel deploy
- quota: use native rpcgen and a single-word RPCGEN\_CPP
- rootfs: move tasks using image\_list\_installed\_packages to postuninstall
- scripts/install-buildtools: Update to 6.0.2
- selftest: uboot: remove duplicated KVM presence test

- socat: upgrade to 1.8.1.3
- sstate: Reduce native sysroot execution race potential
- strace: remove skip-bpf.patch
- sudo: fix pam-wheel sed for sudo 1.9.17p2 sudoers
- systemd-systemctl-native: disable libpam meson option
- tcl: disable the timer tests in run-ptest
- texinfo: add missing perl module runtime dependencies
- tzdata/tzcode-native: upgrade to 2026c
- u-boot: re-enable RISC-V compressed (c) ISA extension
- util-linux: upgrade to 2.41.5
- vex: remove obsolete semicolon
- wic: upgrade to 0.3.1
- xmlto: correct srcrev to point to released version
- xmlto: update *SRC\_URI*

### yocto-docs

- brief-yoctoprojectqs/index.rst: fix a replacement typo
- brief-yoctoprojectqs/index.rst: refresh bitbake-setup outputs
- brief-yoctoprojectqs/index.rst: use pip to install bitbake-setup
- bsp-guide/bsp.rst: fix raspberry layer content example
- contributor-guide: Note patch complexity requirements for stable branches
- dev-manual/creating-fragments.rst: fix typos
- dev-manual/wic.rst: add a requirement to use wic from the build system
- dev-manual/wic.rst: add where to set IMAGE\_FSTYPES/WKS\_FILE[S] from
- dev-manual/wic.rst: convert code snippet to code-blocks
- dev-manual/wic.rst: remove bullet point on host requirements
- dev-manual/wic.rst: remove note on wic-tools
- dev-manual/wic.rst: replace deprecated wks directories
- dev-manual: Fix missing whitespace around '=' operator
- dev-manual: update bmaptool section, refer to "bmaptool" package
- docs-wide: fix broken path links
- docs-wide: fix various broken links
- docs-wide: remove CROPS references

- migration-guide: 5.1: Fix typo
- migration-guide: add release notes for 5.0.19 and 6.0.2
- migration-guides/migration-3.4.rst: replace rlbl broken link
- migration-guides/migration-6.0.rst: fix wks file move note
- migration-guides/release-notes-3.4.2.rst: fix a broken link
- migration-guides/release-notes-5.0.rst: remove broken link
- migration-guides: add add release notes for 6.0.1
- migration-guides: replace broken link with archive links
- recipe-style-guide: Clarify when License-Update tag is needed
- ref-manual/classes.rst: replace deprecated wks directory
- ref-manual/classes.rst: replace obsolete mailing list thread
- ref-manual/images.rst: update obsolete VMWare links
- ref-manual/kickstart.rst: document the include directive
- ref-manual/kickstart.rst: remove note on available commands
- ref-manual/kickstart.rst: replace deprecated wks directory
- ref-manual/release-process.rst: update LTS supported versions
- ref-manual/variables.rst: document missing CONFLICT\_\*\_FEATURES variables
- ref-manual/variables.rst: document the *CCACHE\_NATIVE\_RECIPES\_ALLOWED* variable
- ref-manual/variables.rst: document the IMAGE\_\*\_DEBUGFS variables
- ref-manual/variables.rst: document the *LOCALE\_PATHS* variable
- ref-manual/variables.rst: document the LOCALE\_UTF8\_IS\_DEFAULT variable
- ref-manual/variables.rst: document the *QB\_DEFAULT\_BIOS* variable
- ref-manual/variables.rst: document the *TEST\_SERIALCONTROL\_CONNECT\_TIMEOUT* variable
- ref-manual/variables.rst: document the TEST\_SERIALCONTROL\_PS1 variable
- ref-manual: Fix occurrences of omitted space with :prepend
- ref-manual: add "KERNEL\_IMAGE\_STRIP\_EXTRA\_SECTIONS" to variables
- ref-manual: expand on kernel "do\_sizecheck" task
- ref-manual: fix incorrect heading level for site.conf section
- ref-manual: remove all traces of "kernel\_menuconfig" task
- ref-manual: under meta/files entry, mention Wic files

### **Known Issues in Yocto-6.0.3**

- N/A

### **Contributors to Yocto-6.0.3**

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Adrian Freihofer
- Alexander Kanavin
- Amaury Couderc
- Anil Dongare
- Anton Skorup
- Antonin Godard
- AshishKumar Mishra
- Ashishkumar Parmar
- Benjamin Robin (Schneider Electric)
- Bruce Ashfield
- Daniel Turull
- Darsh Kelaiya
- David Nyström
- Deepak Rathore
- Deepesh Varatharajan
- Devansh Patel
- Eilís 'pidge' Ní Fhlannagáin
- Eric Meyers
- Ernest Van Hoecke
- Gustavo Henrique Nihei
- Hiago De Franco
- Himanshu Jadon
- Hitendra Prajapati
- Jaipaul Cheernam
- Jinwang Li
- João Marcos Costa
- Khem Raj

- Kris Gavvala
- Lee Chee Yang
- Leonid Iziumtsev
- Marek Vasut
- Mengshi Wu
- Nate Kent
- Niko Mauno
- Otavio Salvador
- Paul Barker
- Peter Kjellerstedt
- Peter Marko
- Pritam Srichandan Sahoo
- Richard Purdie
- Robert P. J. Day
- Roland Kovacs
- Ross Burton
- Ryan Eatmon
- Sai Sneha
- Shubham Pushpkar
- Siddharth Doshi
- Siva Balasubramanian
- Sudhir Dumbhare
- Theo Gage (Schneider Electric)
- Ulrich Ölmann
- Vijay Anusuri
- Walter Werner Schneider
- Wei Deng
- Wei Gao
- Wes Malone
- Xiaozhan Li
- Xiuzhuo Shang
- Yoann Congal

- [jaekyu.lee](#)
- [mark.yang](#)

## Repositories / Downloads for Yocto-6.0.3

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [wrynose](#)
- Tag: [yocto-6.0.3](#)
- Git Revision: [5b1ff88511d90634bb3077b878176de577464e12](#)
- Release Artefact: [yocto-docs-5b1ff88511d90634bb3077b878176de577464e12](#)
- sha: [f686c225af0ef33d4607dc03f090c77b0963dc8f15d750c886004786f4297454](#)
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.3/yocto-docs-5b1ff88511d90634bb3077b878176de577464e12.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.3/yocto-docs-5b1ff88511d90634bb3077b878176de577464e12.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [wrynose](#)
- Tag: [yocto-6.0.3](#)
- Git Revision: [ef022bf82d79015802309d14c28b13373ebe53f5](#)
- Release Artefact: [oecore-ef022bf82d79015802309d14c28b13373ebe53f5](#)
- sha: [f43213e9e658cbf3d3c1fd1fe6b68e1a915eb5aec43a0b568387752a9948955e](#)
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.3/oecore-ef022bf82d79015802309d14c28b13373ebe53f5.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.3/oecore-ef022bf82d79015802309d14c28b13373ebe53f5.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: [wrynose](#)
- Tag: [yocto-6.0.3](#)
- Git Revision: [1b132647002eea43a2c7a7f857f63f42dacbc26c](#)
- Release Artefact: [meta-yocto-1b132647002eea43a2c7a7f857f63f42dacbc26c](#)



- sha: 15fa3132056f68e0f4188193bea2ee28dada614ef432a1b2c306d8b1d8141888

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.3/meta-yocto-1b132647002eea43a2c7a7f857f63f42dacbc26c.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.3/meta-yocto-1b132647002eea43a2c7a7f857f63f42dacbc26c.tar.bz2>

bitbake

- Repository Location: <https://git.openembedded.org/bitbake>

- Branch: 2.18

- Tag: yocto-6.0.3

- Git Revision: fae9db3168dbff1b8c76fe9c6726a9687ff97514

- Release Artefact: bitbake-fae9db3168dbff1b8c76fe9c6726a9687ff97514

- sha: 3e338310f008dfb9e8e26a22f44fdf89aa72188acc549905a5cf70a7c4797310

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-6.0.3/bitbake-fae9db3168dbff1b8c76fe9c6726a9687ff97514.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-6.0.3/bitbake-fae9db3168dbff1b8c76fe9c6726a9687ff97514.tar.bz2>

## 17.4 Release 5.3 (whinlatter)

### 17.4.1 Release 5.3 (whinlatter)

#### Migration notes for 5.3 (whinlatter)

This section provides migration information for moving to the Yocto Project 5.3 Release (codename "whinlatter") from the prior release.

#### The Poky repository master branch is no longer updated

The master branch of the [Poky](#) repository is no longer being updated. This does *not* mean that the [Poky](#) distribution is deprecated, but that the way to clone the base layers and setup the environment for building [Poky](#) has changed.

You can either:

- Switch to individual clones of [bitbake](#), [openembedded-core](#), [meta-yocto](#) and [yocto-docs](#) by following the [Setting Up the Poky Reference Distro Manually](#) section of the Yocto Project Development Tasks Manual.
- Use the new `bitbake-setup` tool by following the [Build Rapida di un'Immagine con lo Yocto Project](#) document.

See the [Setting Up The Environment With bitbake-setup](#) of the BitBake User Manual for reference documentation on `bitbake-setup`.

Releases older than Whinlatter will still have their branch on the Poky repository updated until they reach end-of-life.

Some further information on the background of this change can be found in: <https://lists.openembedded.org/g/openembedded-architecture/message/2179>

### **WORKDIR changes**

**`S = ${WORKDIR}/something` no longer supported**

If a recipe has `S` set to be `${WORKDIR}/something`, this is no longer supported, and an error will be issued. The recipe should be changed to:

```
S = "${UNPACKDIR}/something"
```

**`S = ${WORKDIR}/git` and `S = ${UNPACKDIR}/git` should be removed**

The Git fetcher now unpacks into the `BB_GIT_DEFAULT_DESTSUFFIX` directory rather than the `git/` directory under `UNPACKDIR`. `BB_GIT_DEFAULT_DESTSUFFIX` is set in *OpenEmbedded-Core (OE-Core)*'s `bitbake.conf` to `BP`.

This location matches the default value of `S` set by `bitbake.conf`, so `S` setting in recipes can and should be removed.

Note that when `S` is set to a subdirectory of the git checkout, then it should be instead adjusted according to the previous point:

```
S = "${UNPACKDIR}/${BP}/something"
```

Note that "git" as the source checkout location can be hardcoded in other places in recipes; when it's in `SRC_URI`, replace with `BB_GIT_DEFAULT_DESTSUFFIX`, otherwise replace with `BP`.

### **How to make those adjustments without tedious manual editing**

The following sed command can be used to remove `S = "${WORKDIR}/git` across a whole layer:

```
sed -i "/^S = \"\${WORKDIR}\$/git\"/d" `find . -name '*.bb' -o -name '*.inc' -o -  
↪name '*.bbclass'`
```

Then, the following command can tweak the remaining `S` assignments to refer to `UNPACKDIR` instead of `WORKDIR`:

```
sed -i "s/^S = \"\${WORKDIR}\$/S = \"\${UNPACKDIR}\$/g" `find . -name '*.bb' -o -  
↪name '*.inc' -o -name '*.bbclass'`
```

The first change can introduce a lot of consecutive empty lines, so those can be removed with:

```
sed -i -z -E 's/([\t\f\v\r]*\n){3,}/\n\n/g' `find . -name '*.bb' -o -name '*.inc'`
```

### BitBake Git fetcher `tag` parameter

The `tag=` parameter of the Git fetcher (`git://`) was updated. The tag commit SHA will be compared against the value supplied by the `SRCREV` variable or the `rev=` parameter in the URI in `SRC_URI`. This is strongly recommended to add to the URIs when using the Git fetcher for repositories using tag releases.

### Space around equal assignment

A new warning is now printed when there are no whitespaces around an `=` assignment in recipes:

```
<filename>:<line number> has a lack of whitespace around the assignment: '
↪<assignment>'
```

For example, the following assignments would print a warning:

```
FOO="bar"
FOO= "bar"
FOO ="bar"
```

These should be replaced by:

```
FOO = "bar"
```

### Wic plugins containing dashes should be renamed

After a Python upgrade, *Wic* plugins containing dashes (`-`) for their filenames are **no longer supported**. One must rename the plugin file and convert the dashes to underscores (`_`).

It is also recommended to update any WKS file to convert dashes to underscores. For example, the `bootimg-partition.py` plugin was renamed to `bootimg_partition.py`. This means that any WKS file using this plugin must change each `--source bootimg-partition` to `--source bootimg_partition`.

However, the current WIC code automatically converts dashes to underscore for any `--source` call, so existing WKS files will not break if they use upstream plugins from *OpenEmbedded-Core* (*OE-Core*).

### `fitImage` no longer supported for `KERNEL_IMAGETYPE`

The `fitImage` type for `KERNEL_IMAGETYPE` is no longer supported. The logic for creating a FIT image was moved out of the *kernel* class. Instead, one should create a new recipe to build this FIT image, as described in the *Removed Classes* section of the Migration notes for 5.3 (whinlatter).

### systemd Predictable Interface Names no longer MAC policy by default

The *systemd* recipe used to forcibly set the "mac" policy by default when the `pni-names` *distro feature* is enabled.

This is no longer the case as this was not following upstream changes. Now when the `pni-names` *distro feature* is enabled, the default policy from systemd is selected (from <https://github.com/systemd/systemd/blob/v257.8/network/99-default.link>).

To set back the "mac" policy in systemd (version 257.8 at the time of writing this note), you should set the `NamePolicy` and `AlternativeNamesPolicy` as detailed in [systemd.link\(5\)](#).

## Removal of unlicensed Linux kernel firmware

By default, the `linux-firmware` recipe now excludes firmware that do not provide any license information. The recipe holds an internal list of firmware to exclude via a variable named `REMOVE_UNLICENSED`, this variable may be overridden if unlicensed firmware is needed. See [the recipe](#) for a complete overview of the removed firmware.

## \*FLAGS variables behavior change for *native* and *nativesdk* classes

The `CPPFLAGS`, `CFLAGS`, `CXXFLAGS` and `LDFLAGS` variables used to have hard assignments in the *native* and *nativesdk* classes, respectively:

```
CPPFLAGS = "${BUILD_CPPFLAGS}"
CFLAGS = "${BUILD_CFLAGS}"
CXXFLAGS = "${BUILD_CXXFLAGS}"
LDFLAGS = "${BUILD_LDFLAGS}"
```

and:

```
CPPFLAGS = "${BUILDSDK_CPPFLAGS}"
CFLAGS = "${BUILDSDK_CFLAGS}"
CXXFLAGS = "${BUILDSDK_CXXFLAGS}"
LDFLAGS = "${BUILDSDK_LDFLAGS}"
```

This caused races when recipes tried to append to any of these variables using the `+=` operator, so recipes could use `:append` instead if they wanted the change to apply to the target, *native* and *nativesdk* contexts.

Recipes can now safely use the `+=` operator to achieve this.

What this change also means is that previous assignments using the `+=` operator, which only used to apply to the target context, **now apply to all three**: target, *native* and *nativesdk* contexts.

Recipes that unknowingly relied on this behavior should change these assignments to use `TARGET_` variables instead, for example:

```
CFLAGS += "something"
```

to:

```
TARGET_CFLAGS += "something"
```

See <https://git.openembedded.org/openembedded-core/commit/?id=a157b2f9d93428ca21265cc860a3b58b3698b3aa>.

## Supported kernel versions

The `OLDEST_KERNEL` setting is 5.15 in this release, meaning that out the box, older kernels are not supported. See *4.3 migration notes* for details.

## Supported distributions

Compared to the previous releases, running BitBake is supported on new GNU/Linux distributions:

- Debian 13 (Trixie)
- Fedora 42
- Ubuntu 25.04
- Ubuntu 25.10

See *all supported distributions*.

## Removed variables

The following variables have been removed:

- `BUILDHISTORY_RESET`: Setting this to non-empty used to remove the old content of the *buildhistory* as part of the current *BitBake* invocation and replace it with information about what was built during the build. This was partly broken and hard to maintain.
- `GPE_MIRROR`: this variable used to contain the "<https://web.archive.org/web/20160319203545/http://gpe.linuxtogo.org/download/source/>" URL, but was not used by any recipe in OE-Core.

## Removed recipes

The following recipes have been removed in this release:

- `libsoup-2.4`: The last user in *OpenEmbedded-Core (OE-Core)* was `gst-examples`, which has been upgraded with its `libsoup-2.4` dependency dropped. The recipe has been moved to `meta-oe`.
- `glibc-y2038-tests`: removed as the recipe only provides tests which are now provided by `glibc-testsuite`.
- `python3-ndg-httpsclient`: The last dependency in core on this recipe was removed in May 2024 with `dfa482f1998` ("python3-requests: cleanup RDEPENDS"), and there is no other user of this variable.
- `xf86-input-mouse`: The project has stopped supporting Linux.
- `xf86-input-vmmouse`: It has a runtime dependency on `xf86-input-mouse`, which stopped supporting Linux.
- `babeltrace`: Removed in favour of `babeltrace2`.
- `cwautomacros`: A long-obsolete set of custom *autotools*\* macros, not used by any other recipe.
- `rust-llvm`: removed after the Rust and LLVM recipes were reworked to depend on the `llvm` recipe instead.

## Removed *PACKAGECONFIG* entries

- dropbear: enable-x11-forwarding (renamed to x11)
- libxml2: ipv6
- squashfs-tools: reproducible
- mesa: kmsro, osmesa, xa
- systemd: dbus

## Removed classes

The following classes have been removed in this release:

- kernel-fitimage.bbclass: the class has been replaced by the *kernel-fit-image* class. The new implementation resolves the long-standing [bug 12912](#).

If you are using the kernel FIT image support, you will need to:

1. Make sure to include `kernel-fit-extra-artifacts` in your *KERNEL\_CLASSES* variable to ensure the required files are exposed to the *DEPLOY\_DIR\_IMAGE* directory:

```
KERNEL_CLASSES += "kernel-fit-extra-artifacts"
```

2. Use the specific FIT image recipe rather than the base kernel recipe. For example, instead of:

```
bitbake linux-yocto
```

the FIT image is now build by:

```
bitbake linux-yocto-fitimage
```

For custom kernel recipes, creating a corresponding custom FIT image recipe is usually a good approach.

3. If a FIT image is used as a replacement for the kernel image in the root filesystem, add the following configuration to your machine configuration file:

```
# Create and deploy the vmlinux artifact which gets included into the FIT_
↪image
KERNEL_CLASSES += "kernel-fit-extra-artifacts"

# Do not install the kernel image package
RRECOMMENDS:${KERNEL_PACKAGE_NAME}-base = ""

# Install the FIT image package
MACHINE_ESSENTIAL_EXTRA_RDEPENDS += "linux-yocto-fitimage"

# Configure the image.bbclass to depend on the FIT image instead of only
# the kernel to ensure the FIT image is built and deployed with the image
KERNEL_DEPLOY_DEPEND = "linux-yocto-fitimage:do_deploy"
```

See the [kernel-fit-image](#) section for more information.

- `icecc.bbclass`: Reports show that this class has been broken since Yocto Mickledore which suggests there are limited numbers of users. It doesn't have any automated testing and it would be hard to setup and maintain a testing environment for it. The original users/maintainers aren't using it now.

### Miscellaneous changes

- `xserver-xorg`: remove sub-package `${PN}-xwayland`, as `xwayland` is now its own recipe.
- `gdk-pixbuf`: drop the `GDK_PIXBUF_LOADERS` variable, which was part of the recipe's `PACKAGECONFIG`. Instead the `PACKAGECONFIG` can be modified directly to achieve the same result.
- Remove the `meta/conf/distro/include/distro_alias.inc` include file, which associated a recipe name to one or more Distribution package name. This file is not used and maintained anymore.
- Remove the `nghttp2-proxy` package from the `nghttp2` recipe as the `nghttp2-proxy` package became empty after an upgrade that makes it a library recipe only (due to `EXTRA_OEMAKE` containing `-DENABLE_APP=OFF` by default in the recipe).
- Remove the `util-linux-fcntl-lock` package (in the `util-linux` recipe) as `util-linux` now supports the `--fcntl` flag for the `flock` command.

Recipes currently using the `fcntl-lock` command should replace these by `flock --fcntl`.

- `barebox` has been updated from v2025.02.0 to v2025.09.0. Refer to the [upstream migration guides](#) for migration advice.

## 17.4.2 Release notes for 5.3 (whinlatter)

This release does have significant changes which people need to be aware of. See [the migration guide](#) for more information.

### New Features / Enhancements in 5.3

- Linux kernel 6.16, gcc 15, glibc 2.42, LLVM 21.1.1, and over 300 other recipe upgrades.
- Minimum Python version required on the host: 3.9.
- Host requirements changes:
  - The minimum disk space requirement is now 140Gbytes (previously 90Gbytes).
  - The minimum RAM requirement is now 32Gbytes (previously 8Gbytes).
  - These changes are mainly due to recent additions of the LLVM and other resource heavy recipes. For guidance on how to limit the resources used by the *OpenEmbedded Build System*, see the [Limiting the Host Resources Usage](#) guide.
- BitBake changes:
  - A new `bitbake-setup` tool can be used to clone the initial layers and setup the environment. See the [Build Rapida di un'Immagine con lo Yocto Project](#) section for instructions on how to build an image that uses the *Poky* distribution with this new tool.

See the reference documentation of `bitbake-setup` at [Setting Up The Environment With `bitbake-setup`](#).

- `codeparser`: Add function decorators for `vardeps`

Adds `bb.parse.vardeps` and `bb.parse.excludevardeps` function decorators that can be used to explicitly add or exclude variables from a Python function parsed by *BitBake*.

Move `vardepexclude` flag entries alongside functions for maintainability.

- `Fetcher`:

- \* Check for `git-lfs` existence before using it.
- \* Add support for `.debs` files containing uncompressed data tarballs.
- \* `az`: Add sanity check to check that `AZ_SAS` starts with `?` to mark the start of the query parameters.
- \* `git`:
  - Add the tag to shallow clone tarball name.
  - Verify if local clones contains a tag, when the `tag=` parameter is used in `SRC_URI`.

- `knotty`:

- \* Pass failed task logs through the log infrastructure (use `bb.plain()` instead of `print()`).
- \* Improve refresh rate of the footer progress bar.

- Add support for automatically promoting class inherits to deferred inherits by listing them in the `BB_DEFER_BBCLASSES` variable.

- "Built-in" fragments support is now added to the `addfragments` directive. This is the fourth parameter to this directive, and should be the name of the variable that contains definitions of built-in fragments. Refer to the documentation of `addfragments` to learn how to define new built-in fragments.

Listing these built-in fragments can be done with `bitbake-config-build list-fragments`, which could list:

```
Available built-in fragments:
machine/...      Sets MACHINE = ...
distro/...       Sets DISTRO = ...
```

In the above example, this means that the *MACHINE* of *DISTRO* can be overridden with:

```
OE_FRAGMENTS += "machine/qemuarm64 distro/poky-bleeding"
```

This would set *MACHINE* to `qemuarm64` and the *DISTRO* to `poky-bleeding`.

- The `tag=` parameter in URLs can now be specified alongside the `rev=` parameter and `SRCREV` variable, and will ensure that the specified tag matches the specified revision.

It is **strongly encouraged** to include the `tag=` parameter to the `SRC_URI` definition when possible.

- `tinfoil`: add a `wait_for` decorator to wrap a function that makes an asynchronous `tinfoil` call wait for event to say that the call has been successful, or an error has occurred.



- New `bb.utils.to_filemode()` helper function which is a helper to take a variable's content containing a filemode and convert it to the proper Python representation of the number.
- `cooker`: Use a shared counter for processing parser jobs. This allows the parser processes to run independently of needing to be feed by the parent process, and load balances them much better.
- `cooker/process/utils`: Add a `-P (--profile)` option to *BitBake* to specify what to profile. Can be "main", "idle" or "parsing". Split the reports in separate files.
- A "filtering" functionality was added and allows modifying the value of a variable before its value is returned by *BitBake*. The `setVarFilter` API can be used for applying the filters, but it is **not** recommended for general use. It was added for internal use in the *OpenEmbedded Build System* in the *native* class. The list of filters that are allowed are derived from a select list of functions that must be added using a `filter_proc` decorator.
- `tests/parse`: Add tests for `include`, `require` and `include_all`.

- Toolchain changes:

- The Clang/LLVM toolchain can now be used as part of the build.

The `PREFERRED_TOOLCHAIN_TARGET`, `PREFERRED_TOOLCHAIN_NATIVE` and `PREFERRED_TOOLCHAIN_SDK` variables can be used to customize the selected toolchain globally.

There are two supported toolchains: "gcc" and "clang". See the documentation of `PREFERRED_TOOLCHAIN_TARGET` for more details.

The toolchain is also customizable on a per-recipe basis, using the `TOOLCHAIN` and `TOOLCHAIN_NATIVE` variables.

#### Avvertimento

The `TOOLCHAIN` should **not** be set globally. For overriding the toolchain globally, use `PREFERRED_TOOLCHAIN_TARGET`, `PREFERRED_TOOLCHAIN_NATIVE` and `PREFERRED_TOOLCHAIN_SDK`.

- Multiple recipes were pinned to use the GCC/Binutils toolchain as they do not support being built with Clang/LLVM yet. In these recipes the `TOOLCHAIN` variable is set to "gcc".

- Global configuration changes:

- `bitbake.conf/pseudo`: Switch from exclusion list to inclusion list by swapping `PSEUDO_IGNORE_PATHS` for `PSEUDO_INCLUDE_PATHS` which should be easier and more explicit to maintain.
- `bitbake.conf`: Drop `lz4` from `HOSTTOOLS`, as it is not required anymore, and the `lz4-native` package is used instead.
- *Configuration Fragments*:
  - \* Add a fragment for the *CDN sstate-cache* mirror.

- \* Add a `show-fragments` sub-command to the `bitbake-config-build` utility, to show the content of fragments from command-line.
- `default-distrovars`: set an empty default for `LICENSE_PATH`.
- The default definition of `UNPACKDIR` is no longer `sources-unpack` but `sources`.
- The default value for `IMAGE_FSTYPES` (defined in `bitbake.conf`) is now `tar.zst` (previously `tar.gz`).
- Remove the `meta/conf/distro/include/distro_alias.inc` include file, which associated a recipe name to one or more Distribution package name. This file is not used and maintained anymore.
- A new configuration file `build/conf/toolcfg.conf` is now used by `bitbake-config-build` to manage *Configuration Fragments*.
- `bitbake.conf`: add `TMPDIR` to the `GIT_CEILING_DIRECTORIES` Git variable. This avoids Git trying to find a repository higher than `TMPDIR` in recipes that use the `build/tmp/work-shared/` directory for storing their sources. This fixes reproducibility issues.
- Changes to the `genericarm64` machine configuration:
  - \* Increase the `Initramfs` maximum size.
  - \* Install extra Linux firmware packages to fix Linux kernel warnings.
- New variables:
  - The `VIRTUAL-RUNTIME_dbus` variable, to allow changing the runtime implementation of D-Bus. See *VIRTUAL-RUNTIME*.
  - The `VIRTUAL-RUNTIME_libsdl2` variable, to allow changing the runtime implementation of `libsdl2`. See *VIRTUAL-RUNTIME*.
  - The `SPDX_PACKAGE_URL` variable can be used in recipes to set the output `software_packageUrl` field in their associated SPDX 3.0 output (default value: empty string).
  - The `KMETA_CONFIG_FEATURES` variable can be used to control *kernel-yocto* configuration features. For now only `prefer-modules` is supported for this variable.
  - The `TESTSDK_SUITES` variable can be used to control the list of tests run for the *testsdk* class.
  - The `UBOOT_FIT_CONF_FIRMWARE` can be used to specify a `firmware` entry in the configuration node of a FIT image.
  - The `SPDX_INCLUDE_COMPILED_SOURCES` option allows the same as `SPDX_INCLUDE_SOURCES` but including only the sources used to compile the host tools and the target packages.
  - The `UBOOT_VERSION` variable holds the package version (*PV*) and revision (*PR*) which are part of the installed and deployed filenames. Users can now override `UBOOT_VERSION` to changes the output filenames.
  - The `UBOOT_MAKE_OPTS` variable specifies extra options passed to `make` when building U-boot. Extra options can also be passed as the fourth argument of the `UBOOT_CONFIG` variable. See the documentation of *uboot-config* class for more details.
  - The `WESTON_USER` and `WESTON_USER_HOME` variables can be used to define the username and home directory for the *Weston* user.

- New core tasks:
  - The *do\_list\_image\_features* can be used to list the available *IMAGE\_FEATURES* for an image recipe.
- Kernel-related changes:
  - Support for the 6.17 kernel exists but 6.16 is the default selected one in the *Poky* distro.
  - linux/generate-cve-exclusions: use data from CVEProject instead of the archived <https://linuxkernelcves.com> (see <https://web.archive.org/web/20240420122324/https://www.linuxkernelcves.com/>).
  - kernel-yocto: allow annotated options to be modified. For example if the following kernel configuration is set:
 

```
CONFIG_INET_TUNNEL=y # OVERRIDE:$MODULE_OR_Y
```

And if the *KMETA\_CONFIG\_FEATURES* variable contains `prefer-modules`, `CONFIG_INET_TUNNEL` will be set to `m` instead of `y`.
  - kernel-devsrc: Replace the extra `System.map` file with symbolic link.
  - kernel-module-split: Allow for external configuration files being assigned to the correct kernel module package.
  - When built for the RISC-V architecture, ensure that the minimum required features set by *TUNE\_FEATURES* are set using the *features\_check* class.
  - linux-yocto: when built for RISC-V, enable features in *KERNEL\_FEATURES* based on features listed in *TUNE\_FEATURES*.
  - perf: Enable `coresight` if enabled in *MACHINE\_FEATURES*.
- New core recipes:
  - python3-pdm, python3-pdm-backend and python3-pdm-build-locked, which are dependencies of python3-webcolors. python3-pdm itself depends on python3-pdm-build-locked
  - bindgen-cli: a tool to generate Rust bindings.
  - python3-colorama: Cross-platform colored terminal text, needed by `pytest` as a dependency.
  - libglvnd: imported from *meta-oe* which provides a vendor neutral approach to handling OpenGL / OpenGL ES / EGL / GLX libraries.
  - python3-sphinx-argparse: A sphinx extension that automatically documents `argparse` commands and options. It is part of *buildtools-docs-tarball* for later use in the Yocto Project documentation.
  - python3-sphinx-copybutton: A sphinx extension that adds a copy button to code blocks in Sphinx. It is part of *buildtools-docs-tarball* for later use in the Yocto Project documentation.
  - python3-coherent-licensed: License management tooling for *Coherent System* and skeleton projects. It became a new dependency of `python3-zipp`.
  - gn: a commonly used build tool to generate *ninja* files.
  - LLVM/Clang related recipes:

- \* `clang`: LLVM based C/C++ compiler.
  - \* `compiler-rt`: LLVM based C/C++ compiler Runtime.
  - \* `libclc`: Implementation of the library requirements of the OpenCL C programming language.
  - \* `libcxx`: new implementation of the C++ standard library, targeting C++11 and above
  - \* `llvm-tblgen-native`: LLVM TableGen binaries for the build host, often used to build LLVM projects.
  - \* `lld`: the LLVM Linker.
  - \* `lldb`: LLDB debugger for LLVM projects.
  - \* `llvm-project-source`: canonical git mirror of the LLVM subversion repository.
  - \* `llvm`: The LLVM Compiler Infrastructure.
  - \* `openmp`: LLVM OpenMP compiler Runtime.
- `kernel-signing-keys-native`: this recipe is used in the *kernel-fit-image* class to generate a pair of RSA public/private key. It replaces the `do_generate_rsa_keys` of the *kernel-fit-image* class.
  - New *DISTRO\_FEATURES*:
    - `glvnd`, which enables OpenGL Vendor Neutral Dispatch Library support when using recipes such as `mesa`.
    - `opencl`: support for the OpenCL (Open Computing Language) framework.
  - New core classes:
    - The new *kernel-fit-image* class replaces the previous `kernel-fitimage` class. It has been rewritten and improved to fix [bug 12912](#). See the *Removed Classes* section of the Migration notes for 5.3 (whinlatter) for more details on how to switch to this new class.
    - The new *go-mod-update-modules* class can be used to maintain Go recipes that use a `BPN-go-mods.inc` and `BPN-licenses.inc` and update these files automatically.
    - The new *python\_pdm* class supports building Python recipes with the PDM package and dependency manager.
  - Architecture-specific changes:
    - Rework the RISC-V *TUNE\_FEATURES* to make them based of the RISC-V ISA (Instruction Set Architecture) implementation.

This implements the following base ISAs:

- \* `rv32i`, `rv64i`
- \* `rv32e`, `rv64i`

The following ABIs:

- \* `ilp32`, `ilp32e`, `ilp32f`, `ilp32d`
- \* `lp64`, `lp64e`, `lp64f`, `lp64d`

The following ISA extension are also implemented:

- \* M: Integer Multiplication and Division Extension
- \* A: Atomic Memory Extension
- \* F: Single-Precision Floating-Point Extension
- \* D: Double-Precision Floating-Point Extension
- \* C: Compressed Extension
- \* B: Bit Manipulation Extension (implies Zba, Zbb, Zbs)
- \* V: Vector Operations Extension
- \* Zicsr: Control and Status Register Access Extension
- \* Zifencei: Instruction-Fetch Fence Extension
- \* Zba: Address bit manipulation extension
- \* Zbb: Basic bit manipulation extension
- \* Zbc: Carry-less multiplication extension
- \* Zbs: Single-bit manipulation extension
- \* Zicbom: Cache-block management extension

The existing processors tunes are preserved:

- \* `riscv64 (rv64gc)`
- \* `riscv32 (rv32gc)`
- \* `riscv64nf (rv64imac_zicsr_zifencei)`
- \* `riscv32nf (rv32imac_zicsr_zifencei)`
- \* `riscv64nc (rv64imafd_zicsr_zifencei)`

See [meta/conf/machine/include/riscv/README](#) for more information.

- Add support for new Arm64 instruction sets, which are represented as files to be included in *MACHINE* configuration in *OpenEmbedded-Core (OE-Core)*. The new configuration files are:

- \* `conf/machine/include/arm/arch-armv8-7a.inc`
- \* `conf/machine/include/arm/arch-armv8-8a.inc`
- \* `conf/machine/include/arm/arch-armv9-1a.inc`
- \* `conf/machine/include/arm/arch-armv9-2a.inc`
- \* `conf/machine/include/arm/arch-armv9-3a.inc`

- `arch-mips.inc`: Use `-EB/-EL` for denoting Endianness.
- Enable `riscv32` as supported arch for `musl` systems.
- Powerpc: Use `-maltivec` in compiler flags if `altivec` is in *TUNE\_FEATURES*.
- arm: add a `nocrypto` feature to *TUNE\_FEATURES* to complement the `crypto` feature to explicitly disable cryptographic extensions via *GCC* flags.

This lead to the creation of two new tunes:

- \* `tune-cortexa72-nocrypto`
- \* `tune-cortexa53-nocrypto`

- QEMU / `runqemu` changes:

- Refactor *qemu* functions into library functions (in `lib/oe/qemu.py`).
- The `qemux86-64 MACHINE` now defaults to the `x86-64-v3` micro-architecture level.

The previous default was Core 2 era processors. This change means that the toolchain is configured to build for that level, and QEMU is configured to emulate it.

The v3 level adds support for AVX/AVX2/BMI/BMI2/F16C and other newer instructions which are seeing increasing usage in modern software and add performance benefits. Please see [X86-64 Microarchitecture levels](#) for definition of the levels and lists of Intel/AMD CPUs where support for the instructions was first added.

Note that if QEMU system emulation is used on an x86 build machine with `KVM` enabled, then the build machine's CPU must also be recent enough to support these instructions natively.

- `runqemu`:
  - \* The script can now run compressed images with snapshot mode. For example, with *IMAGE\_FSTYPES* containing `ext4.zst`, you can run:

```
runqemu snapshot ext4.zst <image-recipe>
```

- \* Add support for the `erofs` filesystem.
- \* The *BitBake* environment is now a requirement, and the script cannot run without a successful call to `bitbake -e`.

The script will also raise an error with the `bitbake` command is not found.

- Documentation changes:

- Add documentation on *Configuration Fragments*:
  - \* *Using Configuration Fragments*
  - \* *Creating New Configuration Fragments In Your Build*
- Part of *BitBake* internals are now documented at <https://docs.yoctoproject.org/bitbake/bitbake-user-manual/bitbake-user-manual-library-functions.html>.
- A new *Limiting the Host Resources Usage* guide was created to help users limit the resources used by the *OpenEmbedded Build System*.
- A new *Setting up a Hash Equivalence Server* guide was created to help users setting up a *Equivalenza degli Hash* server.
- The QA checks defined in the *OpenEmbedded Build System* were gathered in *QA Error and Warning Messages*.

- A new *Setting Up the Poky Reference Distro Manually* document was added to instruct how to setup the *Poky* reference distribution manually, after the *master branch of the Poky repository has stopped being updated*.
- Core library changes:
  - Add `license_finder.py`, which was extracted from `recipetool` to be shared for multiple users. Improve its functionalities.
- Go changes:
  - *go-mod-update-modules*: Update license finding to use the new `find_licenses_up` library function.
- Rust changes:
  - The `rust-llvm` recipe has been removed, and the `rust` recipe now uses the same `llvm` recipe as `clang`.
  - Add the `has-thread-local` option to the *rust-target-config* class.
- Wic Image Creator changes:
  - After a Python upgrade, WIC plugins containing dashes (–) for their filenames are **no longer supported**. One must convert the dashed to underscores (–) and update users of the plugins accordingly.  
  
See the *Wic plugins containing dashes should be renamed* section of the Yocto Project 5.3 Migration Guide for more information.
  - `wic`: do not ignore *IMAGE\_ROOTFS\_SIZE* if the Rootfs is modified.
  - Several improvements in WIC selftests.
  - `bootimg_efi.py`: fail build if no binaries are installed.
  - Add new options to the `wic ls`, `cp`, `rm`, and `write` commands:
    - \* `--image-name`: name of the image to use the artifacts from.
    - \* `--vars`: directory with `<image>.env` files that store *BitBake* variables. This directory is usually found in *STAGING\_DIR*.
  - Add the Wic-specific option `--extra-partition-space` to add extra empty space after the space filled by the filesystem in the partition.
  - The Wic-specific option `--extra-space` has a new alias `--extra-filesystem-space`.
  - `bootimg_pcbios`: move Syslinux install into separate functions, to make it easier to add new bootloaders.  
  
The Grub bootloader can now be installed with this Wic plugin.
  - Add the Wic plugin `extra_partition` to install files from the *DEPLOY\_DIR\_IMAGE* directory into an extra non-rootfs partition. See the *IMAGE\_EXTRA\_PARTITION\_FILES* variable for more information.
  - The `--diskid` option was added to allow passing a *MS-DOS* or *GPT*-formatted disk IDs for a partition (for example: `deadbeef-cafe-babe-f00d-cec2ea4eface`).
- SDK-related changes:
  - Include additional information about Meson setting in the SDK environment setup script (host system, CPU family, etc.).

- Add Go to `SDK_TOOLCHAIN_LANGS`, except for the following architecture on which this is not supported:
  - \* RISC-V 32 bits (`rv32`)
  - \* PowerPC
- Image-based SDKs can now include *Zsh* completions by adding the `zsh-completion-pkgs` feature to the *IMAGE\_FEATURES* variable in the image recipe.
- The SDK build is now part of the *buildhistory* difference analysis (`buildhistory-diff` command).
- Testing-related changes:
  - `bitbake/tests/fetch`: Add tests for `git-sm` with `git-lfs`.
  - `bitbake/lib/bb/tests/fetch`: add a test case to ensure Git shallow fetch works for tag containing slashes.
  - *testexport*: capture all tests and data from all layers (instead of the *OpenEmbedded-Core (OE-Core)* layer only).
  - OEQA:
    - \* SDK:
      - Add a test to sanity check that the generated SDK manifest was parsed correctly and isn't empty.
      - Add a test to verify the manifests are generated correctly.
      - Add helpers to check for and install packages.
      - Add check that meson has detected the target correctly.
    - \* Simplify test specification and discovery:
      - Introduce the `TESTSDK_CASE_DIRS` variable to specify test directory types, replacing the need to modify the `default_cases` class member.
      - Discover tests from configured layers using a common discovery pattern (`<LAYER_DIR>/lib/oeqa/<dirname>/cases`) where `<dirname>` is specified in `TESTSDK_CASE_DIRS`.
      - The "buildtools" directories were renamed to follow the common discovery pattern (`<LAYER_DIR>/lib/oeqa/<dirname>/cases`) for consistency across all SDK configurations.
    - \* `selftest/reproducible`: Limit memory used by `diffoscope` to avoid triggering OOM kills.
    - \* Add tests for the *devicetree* class.
    - \* Tests for the *kernel-fit-image* class have been reworked and improved.
    - \* `data.py`: add `skipIfNotBuildArch` decorator, to skip tests if *BUILD\_ARCH* is not in present in the specified tuple.
    - \* `selftest`: add new test for toolchain switching.
    - \* `utils/command`: add a fast-path `get_bb_var()` that uses `bitbake-getvar` instead of `bitbake -e` when there is not `postconfig` argument passed.
    - \* `core/case`: add file exists assertion test case.



- \* `context.py`: use *TEST\_SUITES* if set.
  - \* `runqemu`: add new test for booting compressed images.
  - \* General improvements of the parallelization of tests, namely fixing some tests that could spawn an unlimited number of threads leading to OOM kills.
  - \* A new SDK test is now running for Go after `go` was added to `SDK_TOOLCHAIN_LANGS`.
  - \* Commands sent over SSH (using the `OESSTarget` class) will now error when an SSH failure occurs. It is possible to ignore these errors by passing `ignore_ssh_fails` when executing a command.
- Utility script changes:
    - `sstate-cache-management`: add a `--dry-run` argument
    - `yocto-check-layer`:
      - \* Expect success for `test_patches_upstream_status`. This means that patch files *must* include an `Upstream-Status` to pass with this script.
      - \* Show the *DISTRO* used when running the script.
      - \* *yocto-check-layer* class:
        - Refactor to be extended easily.
        - Add a `check_network_flag` test that checks that no tasks other than *do\_fetch* can access the network.
    - `send-error-report`:
      - \* Respect URL scheme in server name if it exists.
      - \* Drop `--no-ssl` as the server URL specifies it with `http://` or `https://`.
    - `buildstats.py`:
      - \* Extend disk stats support for NVMe and flexible token count.
      - \* Add tracking of network I/O per interface.
    - `buildstats-diff`: find last two Buildstats files if none are specified.
    - `pybootchartgui`:
      - \* visualize `/proc/net/dev` network stats in graphs.
      - \* account for network statistics when calculating extents.
  - Packaging changes:
    - Export `debugsources` in *PKGDESTWORK* as JSON. The source information used during packaging can be use from other tasks to have more detailed information on the files used during the compilation and improve SPDX accuracy.
    - When using the `ipk` and `rpm` package managers, give out more possible reasons about unmatched packages.
- Per esempio:

```
E: Package 'catch2' has no installation candidate
catch2 is a recipe. Its generated packages are: ['catch2-src', 'catch2-dbg
→', 'catch2-staticdev', 'catch2-dev', 'catch2-doc']
Either specify a generated package or set ALLOW_EMPTY:${PN} = "1" in
→catch2 recipe
```

- `package.py`: replace all files unconditionally when copying debug sources (passing `-u` to the `cpio` command in `copydebugsources()`). This improves reproducibility.
- LLVM related changes:
  - Like `gcc-source`, the LLVM project sources are part of `work-shared` under `TMPDIR`. The project codebase is large and sharing it offers performance improvements.
- SPDX-related changes:
  - `spdx30`: Provide `software_packageUrl` field
  - `spdx30_tasks`: Change recipe license to "declared" (instead of "concluded")
  - `create-spdx-2.2`: support to override the version of a package in SPDX 2 through `SPDX_PACKAGE_VERSION`.
- devtool and recipetool changes:
  - Use `lib/oe/license_finder` to extract the license from source code.
  - Calculate source paths relative to `UNPACKDIR`.
  - Allow recipe `create` handlers to specify bitbake tasks to run.
  - `create_go`: Use `go-mod` class instead of `go-vendor`.
  - Go recipes are now generated with help of the new `go-mod-update-modules` class.
  - Add a new `improve_kernel_cve_report.py` script in `scripts/contrib` for post-processing of kernel CVE data.
  - Handle workspaces for multiconfig.
  - Fix upgrade for recipes with Git submodules.
- Patchtest-related changes:
  - Multiple improvements to the tool's `README`.
  - Don't match `BitBake` Python expansions as GitHub usernames (`${@...}` syntax).
- Security changes:
  - `openssl`: add FIPS support. This can be enabled through the `fips PACKAGECONFIG`.
  - The default `Poky` template configuration (`local.conf.sample`) does not define the `allow-empty-password`, `empty-root-password`, and `allow-root-login` in `EXTRA_IMAGE_FEATURES` anymore.
- `Toaster` changes:

- Adapt it for [bitbake-setup](#).
- Remove hard dependency on the *Poky* repository, as its *master branch is no longer updated*.
- `cve-check` class changes:
  - `cve-update-db-native`: FKIE: use Secondary metric if there is no Primary metric.
- New *PACKAGECONFIG* options for individual recipes:
  - `ppp`: `l2tp`, `pptp`
  - `dropbear`: `x11` (renamed from `enable-x11-forwarding`)
  - `gdb`: `source-highlight`
  - `gststreamer1.0-plugins-bad`: `analytics`
  - `mtc-utils`: `ubihealthd-service`
  - `openssl`: `fips`
  - `qemu`: `sdl-image`, `pixman`
  - `wget`: `pcr2`
  - `mesa`: `asahi`, `amd`, `svga`, `teflon`, `nouveau`, `xmlconfig`
  - `dbus`: `traditional-activation`, `message-bus`
  - `cmake`: `debugger`
  - `libcxx`: `unwind-cross`
  - `tiff`: `lerc`
  - `freetype`: `brotli`
  - `gawk`: `pma-if-64bit`
  - `x264`: `ffmpeg`, `openssl`
- `Systemd` related changes:
  - Enable `getty` generator by default by adding `serial-getty-generator` to *PACKAGECONFIG*.
  - Now uses the *USE\_NLS* variable to enable or disable building translations.
  - Fix deduplicated templates and instance lines in preset files when listing both template and instances in *SYSTEMD\_SERVICE*.
  - Stop enabling non-standard MAC policy when using the 'pni-names' feature (part of *DI-STRO\_FEATURES*). Instead, follow what is provided by upstream `systemd`.
  - Install `systemd-sysv-install` when using the `systemd-systemctl-native` recipe.
- *sanity* class changes:
  - *insane*: Move test for invalid *PACKAGECONFIG* to *do\_recipe\_qa*.
  - Add `unimplemented-ptest` detection for cargo-based tests, allowing to detect when a cargo package has available tests that could be enable with *Ptest*.

- Add a test for recipe naming/class mismatches.
- Add a sanity test for "bad" gcc installs on Ubuntu 24.04. The host should install `libstdc++-14-dev` instead of `libgcc-14-dev` to avoid build issues when building *native* with Clang.
- Drop the `var-undefined` QA check as it was not relevant for the variables it was checking, as those are mandatory by default.
- U-boot related changes:
  - *uboot-sign*: Add support for setting firmware property in FIT configuration with `UBOOT_FIT_CONF_FIRMWARE`.
  - *uboot-sign*: Add support for signing U-Boot FIT image without an SPL. The `SPL_DTB_BINARY` variable can be set to an empty string to indicate that no SPL is present.
  - When built for the RISC-V architecture, read the `TUNE_FEATURES` variable to automatically set U-boot configuration options (for example `CONFIG_RISCV_ISA_F`).
  - Improve the way build directories are split when having multiple configurations listed in `UBOOT_CONFIG`. This fixes an issue where two or more of these configurations were using the same directory for building (because these were using the same defconfig file).
- Miscellaneous changes:
  - *dropbear*: The `dropbearkey.service` can now take extra arguments for key generation, through `/etc/default/dropbear`.
  - *initscripts*: add `log_success_msg`/`log_failure_msg`/`log_warning_msg` functions for logging in *initscripts*.
  - *connman*:
    - \* Mark `iptables` and `nftables` feature of `PACKAGECONFIG` mutually incompatible.
    - \* Set `dns-backend` automatically to `systemd-resolved` when `systemd-resolved` is part of `DISTRO_FEATURES`.
  - *uninative*: show errors if installing fails.
  - *meson*: Allow user to override setup command options by exporting `MESON_SETUP_OPTS` in a recipe.
  - *cmake*: Enhance to emit a native toolchain CMake file. This is part of improvements allowing to use `clang` in an SDK.
  - Fix the runtime version of several recipes (they now return the effective version instead of a default string like "Unknown").
  - *module*: add `KBUILD_EXTRA_SYMBOLS` to the install command.
  - *rpm-sequoia*: add *Ptest* support.
  - *libunwind*: disable installation of tests directory with `--disable-tests`, which can be installed with the `libunwind-ptest` package instead.
  - *boost*: add `process` library to the list of built libraries.

- `base-files`: add `nsswitch-resolved.conf`, only installed if `systemd` and `systemd-resolved` is part of *DISTRO\_FEATURES*.
- `nfs-utils`: don't use signals to shut down the NFS server in the associated initscript, instead use `rpc.nfsd 0`.
- `readline`: enable HOME, END, INSERT, and DELETE key bindings in `inputrc`.
- Switch to a new *sstate-cache* CDN (<http://sstate.yoctoproject.org>).
- *sstate*: Apply a proper *umask* when fetching from *SSTATE\_MIRRORS*.
- `kernel-devsrc`: make package version consistent with kernel source (by inheriting *kernelsrc*).
- *externalsrc*: Always ask Git for location of `.git` directory (may be different from the default `${S}/.git`).
- *features\_check*: Add support for *REQUIRED\_TUNE\_FEATURES*.
- `openssh`: limit read access to `sshd_config` file (set its filemode to `0600`).
- `barebox-tools` now installs the `rk-usb-loader` utility.
- The *setuptools3\_legacy* class now supports the *pep517-backend* QA check.
- The *ccache* class now supports using *Ccache* for native recipes when the local build configuration contains:

```
ASSUME_PROVIDED += "ccache-native"
HOSTTOOLS += "ccache"
```

- *python\_pep517*: use `pyproject-build` instead of calling the module with `nativepython3`.
- `dbus-glib`: include the binding tools separately into the `${PN}-tools` package.
- `dbus`: use the *systemd* class to handle the unit files of D-Bus.
- `dpkg`: add *ptest* support.
- `shared-mime-info`: Now uses the *USE\_NLS* variable to enable building translations.
- `p11-kit`: Now uses the *USE\_NLS* variable to enable building translations.
- `babeltrace2`: Enable Python plugins
- `initramfs-framework`: mount a temporary filesystem on `/run` and move it to the root filesystem directory before calling `switch_root`.
- `python3`: Pass *PLATFORM\_TRIPLET* explicitly when cross compiling to make the build deterministic instead of letting Python detect the platform triplet (`${HOST_ARCH}-${HOST_OS}`).
- `pulseaudio`: Add the `audio` group explicitly if `pulseaudio-server` is used.
- `oe/license_finder`: Add `find_licenses_up` function to find licenses upwards until reaching a predefined top directory (as an argument).
- `mesa`:
  - \* Build Mesa's Asahi tools when `asahi` is part of the recipe's *PACKAGECONFIG* variable.

- \* The `mesa` recipe now declares two new *PROVIDES* for Vulkan and OpenCL ICD. These virtual provider are respectively named `virtual-opengl-icd` and `virtual-vulkan-icd`.
- `mesa-demos`: split info tools to a separate package `mesa-demos-info`.
- `vte`: skip *object-introspection* with Clang on Arm, as it caused build failures.
- `shadow`: Increase the maximum group name length from 24 to 32 (default value provided by upstream recipe, was previously hardcoded to 24).
- `udev-extraconf`: Speed up the `mount.sh` script by passing the block device of interest to `blkid` when getting partition label names.
- `piglit`: enable OpenCL support if `opengl` is part of the *DISTRO* features.

### Known Issues in 5.3

N/A

### Recipe License changes in 5.3

The following changes have been made to the *LICENSE* values set by recipes:

| Recipe                                 | Previous value                                                                                                                             | New value                                                                                                                                             |
|----------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>flac</code>                      | GFDDL-1.2 & GPL-2.0-or-later<br>& LGPL-2.1-or-later &<br>BSD-3-Clause                                                                      | GFDDL-1.3 & GPL-2.0-or-later<br>& LGPL-2.1-or-later &<br>BSD-3-Clause                                                                                 |
| <code>rust</code>                      | (MIT   Apache-2.0) & Unicode-TOU                                                                                                           | (MIT   Apache-2.0) & Unicode-3.0                                                                                                                      |
| <code>vul-<br/>kan-validation-l</code> | Apache-2.0 & MIT                                                                                                                           | Apache-2.0 & MIT & BSL-1.0                                                                                                                            |
| <code>util-linux</code>                | GPL-1.0-or-later & GPL-2.0-only<br>& GPL-2.0-or-later & LGPL-2.<br>1-or-later & BSD-2-Clause & B<br>SD-3-Clause & BSD-4-Clause-UC &<br>MIT | GPL-1.0-or-later & GPL-2.0-only<br>& GPL-2.0-or-later & LGPL-2.<br>1-or-later & BSD-2-Clause & B<br>SD-3-Clause & BSD-4-Clause-UC &<br>MIT & EUPL-1.2 |
| <code>py-<br/>thon3-docutils</code>    | CC0-1.0 & ZPL-2.1 & BSD-2-Clause<br>& GPL-3.0-only                                                                                         | CC0-1.0 & BSD-2-Clause & GPL-3.<br>0-only                                                                                                             |
| <code>tiff</code>                      | <code>libtiff</code>                                                                                                                       | <code>libtiff</code> & BSD-4.3TAHOE                                                                                                                   |
| <code>gawk</code>                      | GPL-3.0-only                                                                                                                               | GPL-3.0-or-later & AGPL-3.<br>0-or-later                                                                                                              |
| <code>go-helloworld</code>             | MIT                                                                                                                                        | BSD-3-Clause                                                                                                                                          |

### Security Fixes in 5.3

The following CVEs have been fixed:

| Recipe        | CVE IDs                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| busybox       | CVE-2025-46394                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| ghostscript   | CVE-2025-59798, CVE-2025-59799, CVE-2025-59800                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| libmicrohttpd | CVE-2025-59777, CVE-2025-62689                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| libpng        | CVE-2025-64505, CVE-2025-64506, CVE-2025-64720, CVE-2025-65018                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| libsndfile1   | CVE-2024-50613, CVE-2025-52194                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| linux-yocto   | CVE-2019-14899, CVE-2021-3714, CVE-2021-3864, CVE-2022-0400, CVE-2022-1247, CVE-2022-4543, CVE-2022-38096, CVE-2023-3397, CVE-2023-3640, CVE-2023-4010, CVE-2023-6238, CVE-2023-6240, CVE-2023-6535, CVE-2023-39176, CVE-2023-39179, CVE-2023-39180, CVE-2024-52560, CVE-2024-57995, CVE-2024-58015, CVE-2024-58074, CVE-2024-58093, CVE-2024-58094, CVE-2024-58095, CVE-2024-58096, CVE-2024-58097, CVE-2025-4598, CVE-2025-21709, CVE-2025-21751, CVE-2025-21752, CVE-2025-21807, CVE-2025-21833, CVE-2025-21949, CVE-2025-22104, CVE-2025-22105, CVE-2025-22106, CVE-2025-22107, CVE-2025-22108, CVE-2025-22109, CVE-2025-22111, CVE-2025-22116, CVE-2025-22117, CVE-2025-22121, CVE-2025-22127, CVE-2025-23129, CVE-2025-23130, CVE-2025-23131, CVE-2025-23132, CVE-2025-23135, CVE-2025-37743, CVE-2025-37746, CVE-2025-37803, CVE-2025-37860, CVE-2025-37880, CVE-2025-37906, CVE-2025-38029, CVE-2025-38036, CVE-2025-38041, CVE-2025-38042, CVE-2025-38064, CVE-2025-38105, CVE-2025-38132, CVE-2025-38137, CVE-2025-38140, CVE-2025-38187, CVE-2025-38199, CVE-2025-38205, CVE-2025-38207, CVE-2025-38234, CVE-2025-38248, CVE-2025-38261, CVE-2025-38284, CVE-2025-38311, CVE-2025-38359, CVE-2025-38426, CVE-2025-38584, CVE-2025-38591, CVE-2025-38597, CVE-2025-38605, CVE-2025-38621, CVE-2025-38627, CVE-2025-38636, CVE-2025-38656, CVE-2025-38678, CVE-2025-39677, CVE-2025-39678, CVE-2025-39745, CVE-2025-39762, CVE-2025-39764, CVE-2025-39789, CVE-2025-40325 |
| qemu          | CVE-2024-6519, CVE-2024-8354                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| webkitgtk     | CVE-2025-43342, CVE-2025-43343                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |

### Recipe Upgrades in 5.3

The following recipes have been upgraded:

| Recipe        | Previous version(s) | New version(s) |
|---------------|---------------------|----------------|
| acpica        | 20240827            | 20250807       |
| alsa-lib      | 1.2.13              | 1.2.14         |
| alsa-tools    | 1.2.11              | 1.2.14         |
| alsa-ucm-conf | 1.2.13              | 1.2.14         |
| alsa-utils    | 1.2.13              | 1.2.14         |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                    | Previous version(s)      | New version(s)       |
|---------------------------|--------------------------|----------------------|
| appstream                 | 1.0.4                    | 1.0.6                |
| apr                       | 1.7.5                    | 1.7.6                |
| apt                       | 2.6.1                    | 3.0.3                |
| at-spi2-core              | 2.56.0                   | 2.56.4               |
| autoconf                  | 2.72e                    | 2.72                 |
| automake                  | 1.17                     | 1.18.1               |
| babeltrace2               | 2.1.0                    | 2.1.2                |
| barebox                   | 2025.02.0                | 2025.11.0            |
| barebox-tools             | 2025.02.0                | 2025.11.0            |
| base-passwd               | 3.6.6                    | 3.6.7                |
| bash                      | 5.2.37                   | 5.3                  |
| bc                        | 1.08.1                   | 1.08.2               |
| bind                      | 9.20.11                  | 9.20.15              |
| binutils                  | 2.44                     | 2.45                 |
| binutils-cross            | 2.44                     | 2.45                 |
| binu-<br>tils-cross-canac | 2.44                     | 2.45                 |
| binu-<br>tils-crosssdk    | 2.44                     | 2.45                 |
| binu-<br>tils-testsuite   | 2.44                     | 2.45                 |
| blktrace                  | 1.3.0+git                | 1.3.0                |
| bluez5                    | 5.79                     | 5.85                 |
| bmaptool                  | 3.8.0+git                | 3.9.0+git            |
| boost                     | 1.87.0                   | 1.89.0               |
| boo-<br>st-build-native   | 1.87.0                   | 1.89.0               |
| btrfs-tools               | 6.13                     | 6.17                 |
| build-appliance-          | 15.0.0 (316baad50b45...) | 15.0.0               |
| ca-certificates           | 20241223                 | 20250419             |
| cargo                     | 1.84.1                   | 1.90.0               |
| cargo-c                   | 0.10.5+cargo-0.83.0      | 0.10.16+cargo-0.91.0 |
| ccache                    | 4.11                     | 4.12.1               |
| cmake                     | 3.31.6                   | 4.2.0                |
| cmake-native              | 3.31.6                   | 4.2.0                |
| connman                   | 1.43                     | 1.45                 |
| coreutils                 | 9.6                      | 9.7                  |
| createrepo-c              | 1.2.0                    | 1.2.1                |
| cross-localedef-          | 2.41+git                 | 2.42+git             |
| cups                      | 2.4.11                   | 2.4.14               |
| curl                      | 8.12.1                   | 8.17.0               |

continues on next page



Tabella 5 – continua dalla pagina precedente

| Recipe                   | Previous version(s) | New version(s) |
|--------------------------|---------------------|----------------|
| debianutils              | 5.21                | 5.23.2         |
| debugedit                | 5.1                 | 5.2            |
| dhcpcd                   | 10.2.2              | 10.2.4         |
| diffoscope               | 289                 | 306            |
| diffstat                 | 1.67                | 1.68           |
| diffutils                | 3.11                | 3.12           |
| dnf                      | 4.22.0              | 4.24.0         |
| dos2unix                 | 7.5.2               | 7.5.3          |
| dpkg                     | 1.22.11             | 1.22.21        |
| dropbear                 | 2024.86             | 2025.88        |
| e2fsprogs                | 1.47.1              | 1.47.3         |
| ed                       | 1.21                | 1.22.2         |
| elfutils                 | 0.192               | 0.194          |
| ell                      | 0.74                | 0.80           |
| enchant2                 | 2.8.2               | 2.8.12         |
| epiphany                 | 48.3                | 48.5           |
| erofs-utils              | 1.8.5               | 1.8.10         |
| ethtool                  | 6.11                | 6.15           |
| expat                    | 2.7.2               | 2.7.3          |
| fastfloat                | 8.0.2               | 8.1.0          |
| ffmpeg                   | 7.1.2               | 8.0            |
| flac                     | 1.4.3               | 1.5.0          |
| fmt                      | 11.1.4              | 12.1.0         |
| fontconfig               | 2.15.0              | 2.17.1         |
| gawk                     | 5.3.1               | 5.3.2          |
| gcc                      | 14.3.0              | 15.2.0         |
| gcc-cross                | 14.3.0              | 15.2.0         |
| gcc-cross-canadi         | 14.3.0              | 15.2.0         |
| gcc-crosssdk             | 14.3.0              | 15.2.0         |
| gcc-runtime              | 14.3.0              | 15.2.0         |
| gcc-sanitizers           | 14.3.0              | 15.2.0         |
| gcc-source               | 14.3.0              | 15.2.0         |
| gcr                      | 4.3.1               | 4.4.0.1        |
| gdb                      | 16.2                | 16.3           |
| gdb-cross                | 16.2                | 16.3           |
| gdb-cross-canadi         | 16.2                | 16.3           |
| gdbm                     | 1.24                | 1.26           |
| gettext                  | 0.23.1              | 0.26           |
| get-<br>text-minimal-nat | 0.23.1              | 0.26           |
| ghostscript              | 10.05.1             | 10.06.0        |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                      | Previous version(s)   | New version(s)        |
|-----------------------------|-----------------------|-----------------------|
| gi-docgen                   | 2025.3                | 2025.5                |
| git                         | 2.49.1                | 2.51.2                |
| glib-2.0                    | 2.84.4                | 2.86.1                |
| glib-2.0-initial            | 2.84.4                | 2.86.1                |
| glib-networking             | 2.80.0                | 2.80.1                |
| glibc                       | 2.41+git              | 2.42+git              |
| glibc-locale                | 2.41+git              | 2.42+git              |
| glibc-mtrace                | 2.41+git              | 2.42+git              |
| glibc-scripts               | 2.41+git              | 2.42+git              |
| glibc-testsuite             | 2.41+git              | 2.42+git              |
| glslang                     | 1.4.309.0             | 1.4.328.1             |
| gnu-config                  | 20240823+git          | 20250709+git          |
| gnu-efi                     | 4.0.0                 | 4.0.2                 |
| gnupg                       | 2.5.5                 | 2.5.11                |
| go                          | 1.24.6                | 1.25.4                |
| go-binary-native            | 1.24.6                | 1.25.4                |
| go-cross-canadian           | 1.24.6                | 1.25.4                |
| go-cross-core2-3            | 1.24.6                | 1.25.4                |
| go-crosssdk                 | 1.24.6                | 1.25.4                |
| go-helloworld               | 0.1 (d7b0ac127859...) | 0.1 (8b405629c4a5...) |
| go-runtime                  | 1.24.6                | 1.25.4                |
| gperf                       | 3.1                   | 3.3                   |
| gpgme                       | 1.24.2                | 2.0.1                 |
| grep                        | 3.11                  | 3.12                  |
| gset-tings-desktop-sc       | 48.0                  | 49.1                  |
| gst-devtools                | 1.24.13               | 1.26.7                |
| gst-examples                | 1.18.6                | 1.26.7                |
| gststreamer1.0              | 1.24.13               | 1.26.7                |
| gststreamer1.0-libav        | 1.24.13               | 1.26.7                |
| gststreamer1.0-plugins-bad  | 1.24.13               | 1.26.7                |
| gststreamer1.0-plugins-base | 1.24.13               | 1.26.7                |
| gststreamer1.0-plugins-good | 1.24.13               | 1.26.7                |
| gststreamer1.0-plugins-ugly | 1.24.13               | 1.26.7                |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                     | Previous version(s)         | New version(s)              |
|----------------------------|-----------------------------|-----------------------------|
| gststreamer1.0-python      | 1.24.13                     | 1.26.7                      |
| gststreamer1.0-rtsp-server | 1.24.13                     | 1.26.7                      |
| gststreamer1.0-vaapi       | 1.24.13                     | 1.26.7                      |
| gtk+3                      | 3.24.43                     | 3.24.51                     |
| gtk4                       | 4.18.1                      | 4.18.6                      |
| gzip                       | 1.13                        | 1.14                        |
| harfbuzz                   | 10.4.0                      | 11.5.1                      |
| hwdata                     | 0.393                       | 0.399                       |
| hwlatdetect                | 2.8                         | 2.9                         |
| icu                        | 76-1                        | 77-1                        |
| igt-gpu-tools              | 1.30                        | 2.1                         |
| init-system-helper         | 1.68                        | 1.69                        |
| iproute2                   | 6.13.0                      | 6.17.0                      |
| iputils                    | 20240905                    | 20250605                    |
| iso-codes                  | 4.17.0                      | 4.18.0                      |
| iw                         | 6.9                         | 6.17                        |
| json-glib                  | 1.10.6                      | 1.10.8                      |
| kbd                        | 2.7.1                       | 2.8.0                       |
| kea                        | 2.6.3                       | 3.0.1                       |
| kern-tools-native          | 0.3+git (c8c1f17867d0...)   | 0.3+git (f589e1df2325...)   |
| kexec-tools                | 2.0.30                      | 2.0.31                      |
| kmod                       | 34.1                        | 34.2                        |
| kmscube                    | 0.0.1+git (311eaaaa473d...) | 0.0.1+git (f60e50e887d3...) |
| less                       | 668                         | 685                         |
| libadwaita                 | 1.7.0                       | 1.7.6                       |
| libarchive                 | 3.7.9                       | 3.8.3                       |
| libatomic-ops              | 7.8.2                       | 7.8.4                       |
| libc-test                  | 0+git (18e28496adee...)     | 0+git (f2bac7711bec...)     |
| libcap                     | 2.75                        | 2.77                        |
| libcgroup                  | 3.1.0                       | 3.2.0                       |
| libcomps                   | 0.1.21                      | 0.1.23                      |
| libdnf                     | 0.73.4                      | 0.75.0                      |
| libdrm                     | 2.4.124                     | 2.4.128                     |
| libedit                    | 20250104-3.1                | 20251016-3.1                |
| libevdev                   | 1.13.3                      | 1.13.5                      |
| libffi                     | 3.4.7                       | 3.5.2                       |
| libgcc                     | 14.3.0                      | 15.2.0                      |
| libgcc-initial             | 14.3.0                      | 15.2.0                      |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                | Previous version(s) | New version(s) |
|-----------------------|---------------------|----------------|
| libgcrypt             | 1.11.0              | 1.11.2         |
| libgfortran           | 14.3.0              | 15.2.0         |
| libgit2               | 1.9.0               | 1.9.1          |
| libgloss              | 4.4.0+git           | 4.5.0+git      |
| libgpg-error          | 1.51                | 1.56           |
| libinput              | 1.27.1              | 1.29.1         |
| libjitteren-<br>tropy | 3.6.2               | 3.6.3          |
| libjpeg-turbo         | 3.0.1               | 3.1.2          |
| libmicrohttpd         | 1.0.1               | 1.0.2          |
| libmodulemd           | 2.15.0              | 2.15.2         |
| libnotify             | 0.8.4               | 0.8.6          |
| libnss-nis            | 3.2                 | 3.4            |
| libogg                | 1.3.5               | 1.3.6          |
| libpng                | 1.6.47              | 1.6.50         |
| libproxy              | 0.5.9               | 0.5.10         |
| librepo               | 1.19.0              | 1.20.0         |
| librsvg               | 2.59.2              | 2.61.0         |
| libsdl2               | 2.32.2              | 2.32.10        |
| libsecret             | 0.21.6              | 0.21.7         |
| libslirp              | 4.9.0               | 4.9.1          |
| libsolv               | 0.7.31              | 0.7.35         |
| libstd-rs             | 1.84.1              | 1.90.0         |
| libtheora             | 1.1.1               | 1.2.0          |
| libucontext           | 1.2                 | 1.3.2          |
| libunistring          | 1.3                 | 1.4.1          |
| libunwind             | 1.6.2               | 1.8.3          |
| liburcu               | 0.15.1              | 0.15.3         |
| libusb1               | 1.0.27              | 1.0.29         |
| libuv                 | 1.50.0              | 1.51.0         |
| libwebp               | 1.5.0               | 1.6.0          |
| libwpe                | 1.16.2              | 1.16.3         |
| libxfixes             | 6.0.1               | 6.0.2          |
| libxft                | 2.3.8               | 2.3.9          |
| libxkbcommon          | 1.8.1               | 1.11.0         |
| libxml2               | 2.13.8              | 2.14.6         |
| libxmlb               | 0.3.22              | 0.3.23         |
| libxres               | 1.2.2               | 1.2.3          |
| libxscrnsaver         | 1.2.4               | 1.2.5          |
| lighttpd              | 1.4.77              | 1.4.81         |
| linux-firmware        | 20250311            | 20251111       |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                    | Previous version(s)         | New version(s)                       |
|---------------------------|-----------------------------|--------------------------------------|
| li-<br>nux-libc-headers   | 6.12                        | 6.17                                 |
| linux-yocto               | 6.12.47+git                 | 6.12.55+git, 6.16.11+git, 6.17.6+git |
| li-<br>nux-yocto-dev      | 6.14+git                    | 6.18+git                             |
| linux-yocto-rt            | 6.12.47+git                 | 6.12.55+git, 6.16.11+git, 6.17.6+git |
| li-<br>nux-yocto-tiny     | 6.12.47+git                 | 6.12.55+git, 6.16.11+git, 6.17.6+git |
| llvm                      | 20.1.0                      | 21.1.6                               |
| lsof                      | 4.99.4                      | 4.99.5                               |
| ltp                       | 20250130                    | 20250930                             |
| lttng-modules             | 2.13.17                     | 2.14.3                               |
| lttng-tools               | 2.13.14                     | 2.14.0                               |
| lttng-ust                 | 2.13.8                      | 2.14.0                               |
| lua                       | 5.4.7                       | 5.4.8                                |
| m4                        | 1.4.19                      | 1.4.20                               |
| m4-native                 | 1.4.19                      | 1.4.20                               |
| man-db                    | 2.13.0                      | 2.13.1                               |
| man-pages                 | 6.13                        | 6.15                                 |
| mdadm                     | 4.3                         | 4.4                                  |
| mesa                      | 24.0.7                      | 25.2.5                               |
| mesa-gl                   | 24.0.7                      | 25.2.5                               |
| meson                     | 1.7.0                       | 1.9.1                                |
| mmc-utils                 | 0.1+git                     | 1.0                                  |
| mobi-<br>le-broadband-prc | 20240407                    | 20250613                             |
| mpfr                      | 4.2.1                       | 4.2.2                                |
| mpg123                    | 1.32.10                     | 1.33.2                               |
| msmtp                     | 1.8.28                      | 1.8.31                               |
| musl                      | 1.2.5+git (c47ad25ea3b4...) | 1.2.5+git (0ccaf0572e9c...)          |
| nettle                    | 3.10.1                      | 3.10.2                               |
| newlib                    | 4.4.0+git                   | 4.5.0+git                            |
| nfs-utils                 | 2.8.2                       | 2.8.4                                |
| nghttp2                   | 1.65.0                      | 1.68.0                               |
| ninja                     | 1.12.1                      | 1.13.1                               |
| ofono                     | 2.15                        | 2.18                                 |
| opensbi                   | 1.6                         | 1.7                                  |
| openssh                   | 9.9p2                       | 10.2p1                               |
| openssl                   | 3.4.2                       | 3.5.4                                |
| opkg                      | 0.7.0                       | 0.9.0                                |
| ovmf                      | edk2-stable202411           | edk2-stable202508                    |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                  | Previous version(s)        | New version(s)             |
|-------------------------|----------------------------|----------------------------|
| pango                   | 1.56.2                     | 1.57.0                     |
| patch                   | 2.7.6                      | 2.8                        |
| patchelf                | 0.18.0                     | 0.18.0+git                 |
| pciutils                | 3.13.0                     | 3.14.0                     |
| piglit                  | 1.0+gitr (fc8179d31904...) | 1.0+gitr (a0a27e528f64...) |
| pinentry                | 1.3.1                      | 1.3.2                      |
| pixman                  | 0.44.2                     | 0.46.4                     |
| pkgconf                 | 2.4.3                      | 2.5.1                      |
| pseudo                  | 1.9.0+git                  | 1.9.2+git                  |
| psplash                 | 0.1+git (1f64c654129f...)  | 0.1+git (53ae74a36bf1...)  |
| puzzles                 | 0.0+git (7da464122232...)  | 0.0+git (a7c7826bce5c...)  |
| python3                 | 3.13.4                     | 3.13.9                     |
| py-<br>thon3-beartype   | 0.20.0                     | 0.21.0                     |
| py-<br>thon3-booleanpy  | 4.0                        | 5.0                        |
| python3-build           | 1.2.2                      | 1.3.0                      |
| python3-calver          | 2022.6.26                  | 2025.04.17                 |
| py-<br>thon3-certifi    | 2025.1.31                  | 2025.8.3                   |
| python3-click           | 8.1.8                      | 8.2.2                      |
| py-<br>thon3-cryptograf | 44.0.2                     | 45.0.7                     |
| py-<br>thon3-cryptograf | 44.0.2                     | 45.0.7                     |
| python3-cython          | 3.0.12                     | 3.1.3                      |
| py-<br>thon3-dbusmock   | 0.33.0                     | 0.37.0                     |
| py-<br>thon3-docutils   | 0.21.2                     | 0.22                       |
| py-<br>thon3-dtschema   | 2025.2                     | 2025.8                     |
| py-<br>thon3-flit-core  | 3.11.0                     | 3.12.0                     |
| py-<br>thon3-hatch-fanc | 24.1.0                     | 25.1.0                     |
| py-<br>thon3-hatch-vcs  | 0.4.0                      | 0.5.0                      |
| py-<br>thon3-hypothesis | 6.129.2                    | 6.142.2                    |
| python3-idna            | 3.10                       | 3.11                       |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                | Previous version(s) | New version(s) |
|-----------------------|---------------------|----------------|
| py-thon3-iniconfig    | 2.0.0               | 2.1.0          |
| py-thon3-jjsonschema  | 4.23.0              | 4.25.1         |
| py-thon3-jjsonschema  | 2024.10.1           | 2025.9.1       |
| py-thon3-license-ex   | 30.4.1              | 30.4.4         |
| python3-lxml          | 5.3.1               | 6.0.2          |
| python3-mako          | 1.3.9               | 1.3.10         |
| py-thon3-markdown     | 3.7                 | 3.9            |
| py-thon3-maturin      | 1.8.3               | 1.9.4          |
| py-thon3-meson-python | 0.17.1              | 0.18.0         |
| python3-numpy         | 2.2.3               | 2.3.4          |
| py-thon3-packaging    | 24.2                | 25.0           |
| python3-pbr           | 6.1.0               | 7.0.1          |
| python3-pip           | 25.0.1              | 25.2           |
| python3-pluggy        | 1.5.0               | 1.6.0          |
| py-thon3-poetry-core  | 2.1.1               | 2.1.3          |
| py-thon3-pycairo      | 1.27.0              | 1.28.0         |
| py-thon3-pycryptodome | 3.22.0              | 3.23.0         |
| py-thon3-pycryptodome | 3.22.0              | 3.23.0         |
| py-thon3-pygments     | 2.19.1              | 2.19.2         |
| py-thon3-pyobject     | 3.52.2              | 3.54.5         |
| py-thon3-pyopenssl    | 25.0.0              | 25.1.0         |
| py-thon3-pyparsing    | 3.2.1               | 3.2.4          |
| python3-pytest        | 8.3.5               | 8.4.2          |
| py-thon3-pytest-sugar | 0.14.1              | 0.14.2         |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe                  | Previous version(s) | New version(s) |
|-------------------------|---------------------|----------------|
| python3-pytz            | 2025.1              | 2025.2         |
| python3-rdflib          | 7.1.3               | 7.1.4          |
| py-<br>thon3-referencir | 0.36.2              | 0.37.0         |
| py-<br>thon3-requests   | 2.32.4              | 2.32.5         |
| py-<br>thon3-rpds-py    | 0.22.3              | 0.27.1         |
| py-<br>thon3-ruamel-yan | 0.18.10             | 0.18.15        |
| python3-scons           | 4.9.0               | 4.9.1          |
| py-<br>thon3-setuptools | 76.0.0              | 80.9.0         |
| py-<br>thon3-setuptools | 1.11.0              | 1.12.0         |
| py-<br>thon3-setuptools | 8.2.0               | 8.3.1          |
| py-<br>thon3-smartypant | 2.0.0               | 2.0.2          |
| py-<br>thon3-snowballst | 2.2.0               | 3.0.1          |
| py-<br>thon3-trove-clas | 2025.3.13.13        | 2025.9.11.17   |
| py-<br>thon3-typing-ext | 4.12.2              | 4.15.0         |
| py-<br>thon3-unittest-e | 0.2                 | 0.3            |
| py-<br>thon3-uritools   | 4.0.3               | 5.0.0          |
| py-<br>thon3-urllib3    | 2.3.0               | 2.5.0          |
| py-<br>thon3-webcolors  | 24.8.0              | 24.11.1        |
| python3-wheel           | 0.45.1              | 0.46.1         |
| py-<br>thon3-xmltodict  | 0.14.2              | 0.15.1         |
| py-<br>thon3-yamllint   | 1.36.0              | 1.37.1         |
| python3-zipp            | 3.21.0              | 3.23.0         |
| qemu                    | 9.2.0               | 10.0.6         |
| qemu-native             | 9.2.0               | 10.0.6         |

continues on next page



Tabella 5 – continua dalla pagina precedente

| Recipe              | Previous version(s)   | New version(s)        |
|---------------------|-----------------------|-----------------------|
| qe-                 | 9.2.0                 | 10.0.6                |
| mu-system-native    |                       |                       |
| quilt               | 0.68                  | 0.69                  |
| quilt-native        | 0.68                  | 0.69                  |
| quota               | 4.09                  | 4.10                  |
| re2c                | 4.1                   | 4.3                   |
| readline            | 8.2.13                | 8.3                   |
| repo                | 2.52                  | 2.58                  |
| resolvconf          | 1.92                  | 1.94                  |
| rpcbind             | 1.2.7                 | 1.2.8                 |
| rpm                 | 4.20.0                | 4.20.1                |
| rpm-sequoia         | 1.7.0                 | 1.9.0                 |
| rpm-sequoia-crypt   | git (032b418a6db8...) | git (ae1df75b1155...) |
| rt-tests            | 2.8                   | 2.9                   |
| ruby                | 3.4.4                 | 3.4.5                 |
| rust                | 1.84.1                | 1.90.0                |
| ru-                 | 1.84.1                | 1.90.0                |
| st-cross-canadian   |                       |                       |
| sbc                 | 2.0                   | 2.1                   |
| scdoc               | 1.11.3                | 1.11.4                |
| screen              | 5.0.0                 | 5.0.1                 |
| shaderc             | 2024.3                | 2025.3                |
| shadow              | 4.17.3                | 4.18.0                |
| spirv-headers       | 1.4.309.0             | 1.4.328.1             |
| spirv-tools         | 1.4.309.0             | 1.4.328.1             |
| squashfs-tools      | 4.6.1                 | 4.7.4                 |
| strace              | 6.12                  | 6.17                  |
| stress-ng           | 0.18.11               | 0.19.04               |
| sudo                | 1.9.17p1              | 1.9.17p2              |
| swig                | 4.3.0                 | 4.3.1                 |
| sysklogd            | 2.7.1                 | 2.7.2                 |
| sysstat             | 12.7.7                | 12.7.8                |
| systemd             | 257.6                 | 257.8                 |
| systemd-boot        | 257.6                 | 257.8                 |
| syste-              | 257.6                 | 257.8                 |
| md-boot-native      |                       |                       |
| syste-              | 257.6                 | 257.8                 |
| md-systemctl-native |                       |                       |
| systemtap           | 5.2                   | 5.3                   |
| system-             | 5.2                   | 5.3                   |
| tap-native          |                       |                       |

continues on next page

Tabella 5 – continua dalla pagina precedente

| Recipe           | Previous version(s)   | New version(s)        |
|------------------|-----------------------|-----------------------|
| taglib           | 2.0.2                 | 2.1.1                 |
| tcf-agent        | 1.8.0+git             | 1.9.0                 |
| tcl              | 9.0.1                 | 9.0.2                 |
| tcl8             | 8.6.16                | 8.6.17                |
| tiff             | 4.7.0                 | 4.7.1                 |
| ttyrun           | 2.37.0                | 2.38.0                |
| u-boot           | 2025.01               | 2025.10               |
| u-boot-tools     | 2025.01               | 2025.10               |
| unfs3            | 0.10.0                | 0.11.0                |
| usbutils         | 018                   | 019                   |
| util-linux       | 2.40.4                | 2.41.1                |
| util-linux-libu  | 2.40.4                | 2.41.1                |
| valgrind         | 3.24.0                | 3.25.1                |
| vim              | 9.1.1652              | 9.1.1683              |
| vim-tiny         | 9.1.1652              | 9.1.1683              |
| virglrenderer    | 1.1.0                 | 1.1.1                 |
| vte              | 0.78.2                | 0.82.1                |
| vulkan-headers   | 1.4.309.0             | 1.4.328.1             |
| vulkan-loader    | 1.4.309.0             | 1.4.328.1             |
| vulkan-samples   | git (8547ce1022a1...) | git (d27205d14d01...) |
| vulkan-tools     | 1.4.309.0             | 1.4.328.1             |
| vul-             | 1.4.309.0             | 1.4.328.1             |
| kan-utility-libr |                       |                       |
| vul-             | 1.4.309.0             | 1.4.328.1             |
| kan-validation-l |                       |                       |
| vulkan-volk      | 1.4.309.0             | 1.4.328.1             |
| wayland          | 1.23.1                | 1.24.0                |
| way-             | 1.41                  | 1.45                  |
| land-protocols   |                       |                       |
| webkitgtk        | 2.48.2                | 2.50.0                |
| weston           | 14.0.1                | 14.0.2                |
| which            | 2.21                  | 2.23                  |
| wireless-regdb   | 2025.02.20            | 2025.10.07            |
| xdpyinfo         | 1.3.4                 | 1.4.0                 |
| xin-             | 0.7.5+git             | 0.8.0                 |
| put-calibrator   |                       |                       |
| xkey-            | 2.44                  | 2.45                  |
| board-config     |                       |                       |
| xwayland         | 24.1.6                | 24.1.8                |
| xz               | 5.6.4                 | 5.8.1                 |

## Contributors to 5.3

Thanks to the following people who contributed to this release:

- Adam Blank
- Adam Nilsson
- Adrian Freihofer
- Ahmad Fatoum
- Alejandro Hernandez Samaniego
- Aleksandar Nikolic
- Alexander Kanavin
- Alex Kiernan
- Alon Bar-Lev
- Alper Ak
- Andreas Stergiopoulos
- Andrej Valek
- Anibal Limon
- Ankur Tyagi
- Anna-Lena Marx
- Antonin Godard
- Anuj Mittal
- Archana Polampalli
- Barne Carstensen
- Benjamin Missey
- Benjamin Szőke
- Bo Sun
- Bruce Ashfield
- Carlos Sánchez de La Lama
- Changqing Li
- Chen Qi
- Chris Laplante
- Christian Lindeberg
- Christos Gavros
- Daisuke Yamane

- Daniel McGregor
- Daniel Turull
- Daniel Wagenknecht
- Dan McGregor
- Dario Binacchi
- David Reyna
- Deepak Rathore
- Deepesh Varatharajan
- denisova-ok
- Denys Dmytriyenko
- Diego de los Santos
- Diego Sueiro
- Divya Chellam
- Dixit Parmar
- Dmitry Baryshkov
- Enrico Jörns
- Enrico Scholz
- Erick Shepherd
- Erik Lindsten
- Etienne Cordonnier
- Fabio Estevam
- Falk Bauer
- Gregor Herburger
- Guðni Már Gilbert
- Gyorgy Sarvari
- Haixiao Yan
- Harish Sadineni
- Hiago De Franco
- hongxu
- Hongxu Jia
- Ines KCHELFI
- Isaac True

- Jaeyoon Jung
- Jamin Lin
- Jan Vermaete
- Jason M. Bills
- Jason Schonberg
- Jayasurya Maganuru
- Jeroen Hofstee
- Jiaying Song
- Jimmy Ho
- Jinfeng Wang
- João Henrique Ferreira de Freitas
- Joao Marcos Costa
- João Marcos Costa
- Johannes Schneider
- Jonathan Schnitzler
- Jon Mason
- Jörg Sommer
- Jose Quaresma
- Joshua Watt
- J. S.
- Julian Haller
- Kai Kang
- Kavinaya S
- Keerthivasan Raghavan
- Khang D Nguyen
- Khem Raj
- Koch, Stefan
- Koen Kooi
- Kyungjik Min
- Lamine REHAHLIA
- Lee Chee Yang
- leimaohui

- Lei Maohui
- Leon Anavi
- Leonard Anderweit
- Libo Chen
- Liu Yiding
- Li Wang
- Louis Rannou
- Luca Fancellu
- Madhu Marri
- Manuel Leonhardt
- Marco Cavallini
- Mark Asselstine
- Mark Hatle
- Markus Kurz
- Markus Volk
- Martin Jansa
- Martin Siegumfeldt
- Mathieu Dubois-Briand
- Michael Halstead
- Michael Jeanson
- Michael Opdenacker
- Michael Tretter
- Michal Sieron
- Mike Crowe
- Mike Looijmans
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Moritz Haase
- NeilBrown
- Nguyen Dat Tho
- Nikhil R

- Niko Mauno
- Ola x Nilsson
- Olga Denisova
- Osama Abdelkader
- Osose Itua
- Ovidiu Panait
- Patrick Vogelaar
- Patrick Williams
- Patryk Seregiet
- Paul Barker
- Paul Gortmaker
- Pedro Ferreira
- Per x Johansson
- Peter Kjellerstedt
- Peter Marko
- Peter Tatrai
- Petr Vorel
- Philip Lorenz
- Philippe-Alexandre Mathieu
- Pierre-Loup GOSSE
- Poonam Jadhav
- Praveen Kumar
- Priyal Doshi
- Quentin Schulz
- rajmohan r
- Randolph Sapp
- Randy MacLeod
- Raphael Schlarb
- Rasmus Villemoes
- Ricardo Salveti
- Ricardo Simoes
- Richard Grünert

- Richard Purdie
- Robbin Van Damme
- Robert P. J. Day
- Robert Tiemann
- Robert Yang
- Rogerio Guerra Borin
- Ross Burton
- Ryan Eatmon
- Samuli Piippo
- Sandeep Gundlupet Raju
- Saravanan
- Siddharth Doshi
- Simone Weiß
- Soumya Sambu
- Stefan Eichenberger
- Stefan Koch
- Steffen Greber
- Steve Sakoman
- Talel BELHAJ SALEM
- Thomas Perrot
- Thune Tran
- Tim Orling
- Tobias Pistora
- Tom Hochstein
- Trevor Gamblin
- Trevor Woerner
- Tudor Ambarus
- Uwe Kleine-König
- Veeresh Kadasani
- Victor Kamensky
- Vijay Anusuri
- Vincent Davis Jr



- Vishwas Udupa
- Vivek Puar
- Vyacheslav Yurkov
- Walter Werner SCHNEIDER
- Wang Mingyu
- Weisser, Pascal.ext
- Yannic Moog
- Yash Shinde
- Yi Zhao
- Yoann Congal
- Yogesh Tyagi
- Yogita Urade
- Zhang Peng
- Zoltan Boszormenyi
- Zoltán Böszörményi

### Repositories / Downloads for Yocto-5.3

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3](#)
- Git Revision: [79cd33b06e87c04e4f873a5afd9d53714bc5047f](#)
- Release Artefact: [yocto-docs-79cd33b06e87c04e4f873a5afd9d53714bc5047f](#)
- sha: [f2a353847243370d6924ea83542b055ee8098c51d4875b6a9b2cee79b98c0f29](#)
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-5.3/yocto-docs-79cd33b06e87c04e4f873a5afd9d53714bc5047f.tar.bz2>
  - <https://mirrors.kernel.org/yocto/yocto/yocto-5.3/yocto-docs-79cd33b06e87c04e4f873a5afd9d53714bc5047f.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3](#)
- Git Revision: [8519978592483bb096ed5192fff7af6c887b799e](#)

- Release Artefact: `oecore-8519978592483bb096ed5192fff7af6c887b799e`
- sha: `3b23d8a56a2f6e3872ec01272a76e3551ac1eab001f81c9abc680ce415aa888d`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3/oecore-8519978592483bb096ed5192fff7af6c887b799e.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.3/oecore-8519978592483bb096ed5192fff7af6c887b799e.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `whinlatter`
- Tag: `yocto-5.3`
- Git Revision: `d02d3faaf4d6075ea03e9eb47654ec7639f929a0`
- Release Artefact: `meta-yocto-d02d3faaf4d6075ea03e9eb47654ec7639f929a0`
- sha: `e2a69bf93466cd010fd14e4f1b2bb5f45da165b00eb1fbf7987541d7a9378d47`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3/meta-yocto-d02d3faaf4d6075ea03e9eb47654ec7639f929a0.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.3/meta-yocto-d02d3faaf4d6075ea03e9eb47654ec7639f929a0.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `whinlatter`
- Tag: `yocto-5.3`
- Git Revision: `:yocto_git:`</meta-mingw/commit/?id=00323de97e397d4f6734ef2191806616989f5e10>``
- Release Artefact: `meta-mingw-00323de97e397d4f6734ef2191806616989f5e10`
- sha: `c9a70539b12c0642596fde6a2766d4a6a8fec8b2a366453fb6473363127a1c77`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.3/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.16`

- Tag: `yocto-5.3`
- Git Revision: `720df1a53452983c1c832f624490e255cf389204`
- Release Artefact: `bitbake-720df1a53452983c1c832f624490e255cf389204`
- sha: `08a5d8914b59e904a805fbf0e76058dfeddd49f4a022298a3c1485b98233db24`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3/bitbake-720df1a53452983c1c832f624490e255cf389204.tar.bz2>  
  
<https://mirrors.kernel.org/yocto/yocto/yocto-5.3/bitbake-720df1a53452983c1c832f624490e255cf389204.tar.bz2>

### 17.4.3 Release notes for Yocto-5.3.1 (Whinlatter)

Users of Alma 9, Rocky 9 and Centos Stream 9 rolling releases have seen obtuse failures in the execution of tar in various tasks after recent host distro updates. These newer versions of tar contain a CVE fix which uses a new glibc call/syscall (`openat2`). The fix is to update to a newer pseudo version which handles this syscall. This is not included in this stable release but we aim to include it in the next one.

#### Security Fixes in Yocto-5.3.1

- binutils: Fix CVE-2025-11494, CVE-2025-11839 and CVE-2025-11840
- cups: Fix CVE-2025-58436 and CVE-2025-61915
- dropbear: Fix CVE-2019-6111
- glib-2.0: Fix CVE-2025-13601, CVE-2025-14087 and CVE-2025-14512
- gnutls: Fix CVE-2025-9820
- go: Fix CVE-2025-61727 and CVE-2025-61729
- libarchive: Fix CVE-2025-60753
- libcap: Fix CVE-2025-11961 and CVE-2025-11964
- libpng: Fix CVE-2025-64505, CVE-2025-64506, CVE-2025-64720, CVE-2025-65018 and CVE-2025-66293
- linux-yocto/6.12: Ignore CVE-2023-7324, CVE-2024-57995, CVE-2025-21833, CVE-2025-22105, CVE-2025-22107, CVE-2025-22121, CVE-2025-23129, CVE-2025-23130, CVE-2025-37803, CVE-2025-37860, CVE-2025-38643, CVE-2025-38678, CVE-2025-39678, CVE-2025-39981, CVE-2025-40014, CVE-2025-40026, CVE-2025-40027, CVE-2025-40028, CVE-2025-40029, CVE-2025-40030, CVE-2025-40031, CVE-2025-40032, CVE-2025-40033, CVE-2025-40034, CVE-2025-40035, CVE-2025-40036, CVE-2025-40037, CVE-2025-40038, CVE-2025-40039, CVE-2025-40040, CVE-2025-40041, CVE-2025-40042, CVE-2025-40043, CVE-2025-40044, CVE-2025-40045, CVE-2025-40046, CVE-2025-40047, CVE-2025-40048, CVE-2025-40049, CVE-2025-40050, CVE-2025-40051, CVE-2025-40052, CVE-2025-40053, CVE-2025-40055, CVE-2025-40056, CVE-2025-40057, CVE-2025-40058, CVE-2025-40059, CVE-2025-40060, CVE-2025-40061, CVE-2025-40062, CVE-2025-40063, CVE-2025-40066,

CVE-2025-40067, CVE-2025-40068, CVE-2025-40069, CVE-2025-40070, CVE-2025-40071, CVE-2025-40072, CVE-2025-40073, CVE-2025-40076, CVE-2025-40077, CVE-2025-40078, CVE-2025-40079, CVE-2025-40080, CVE-2025-40081, CVE-2025-40082, CVE-2025-40083, CVE-2025-40084, CVE-2025-40085, CVE-2025-40087, CVE-2025-40088, CVE-2025-40089, CVE-2025-40090, CVE-2025-40091, CVE-2025-40092, CVE-2025-40093, CVE-2025-40094, CVE-2025-40095, CVE-2025-40096, CVE-2025-40097, CVE-2025-40099, CVE-2025-40100, CVE-2025-40101, CVE-2025-40103, CVE-2025-40104, CVE-2025-40105, CVE-2025-40106, CVE-2025-40107, CVE-2025-40108, CVE-2025-40109, CVE-2025-40110, CVE-2025-40111, CVE-2025-40112, CVE-2025-40115, CVE-2025-40116, CVE-2025-40117, CVE-2025-40118, CVE-2025-40119, CVE-2025-40120, CVE-2025-40121, CVE-2025-40122, CVE-2025-40123, CVE-2025-40124, CVE-2025-40125, CVE-2025-40126, CVE-2025-40127, CVE-2025-40129, CVE-2025-40131, CVE-2025-40132, CVE-2025-40133, CVE-2025-40134, CVE-2025-40137, CVE-2025-40138, CVE-2025-40140, CVE-2025-40141, CVE-2025-40142, CVE-2025-40143, CVE-2025-40144, CVE-2025-40145, CVE-2025-40148, CVE-2025-40151, CVE-2025-40152, CVE-2025-40153, CVE-2025-40154, CVE-2025-40155, CVE-2025-40156, CVE-2025-40157, CVE-2025-40159, CVE-2025-40160, CVE-2025-40161, CVE-2025-40162, CVE-2025-40163, CVE-2025-40165, CVE-2025-40166, CVE-2025-40167, CVE-2025-40169, CVE-2025-40171, CVE-2025-40172, CVE-2025-40173, CVE-2025-40174, CVE-2025-40175, CVE-2025-40176, CVE-2025-40177, CVE-2025-40178, CVE-2025-40179, CVE-2025-40180, CVE-2025-40181, CVE-2025-40182, CVE-2025-40183, CVE-2025-40184, CVE-2025-40185, CVE-2025-40186, CVE-2025-40187, CVE-2025-40188, CVE-2025-40189, CVE-2025-40190, CVE-2025-40191, CVE-2025-40192, CVE-2025-40193, CVE-2025-40194, CVE-2025-40195, CVE-2025-40196, CVE-2025-40197, CVE-2025-40198, CVE-2025-40199, CVE-2025-40200, CVE-2025-40201, CVE-2025-40202, CVE-2025-40203, CVE-2025-40204, CVE-2025-40205, CVE-2025-40206, CVE-2025-40207, CVE-2025-40208, CVE-2025-40209, CVE-2025-40211, CVE-2025-40212 and CVE-2025-40213

- python3-urllib3: Fix CVE-2025-66418
- python3: Fix CVE-2025-6075 and CVE-2025-12084
- sqlite3: Fix CVE-2025-3277, CVE-2025-6965 and CVE-2025-29087

## **Fixes in Yocto-5.3.1**

### **bitbake**

- bin: Hide os.fork() deprecation warning in all bitbake scripts
- bitbake-layers: Also hide os.fork() deprecation warning

### **meta-yocto**

- poky.conf: bump version for 5.3.1

### **openembedded-core**

- build-appliance-image: Update to whinlatter head revisions
- ccache: upgrade to 4.12.2
- cross.bbclass: Propagate dependencies to outhash
- cups: upgrade to 2.4.15

- curl: Use host CA bundle by default for native(sdk) builds
- cve-update: Avoid NFS caching issues
- e2fsprogs: misc/create\_inode.c: Fix for file larger than 2GB
- ell: upgrade to 0.80
- enchant2: upgrade to 2.8.14
- glib-2.0: Upgrade to 2.86.1
- glib-2.0: upgrade to 2.86.3
- go: upgrade to 1.25.5
- gst-devtools: upgrade to 1.26.7
- gst-examples: upgrade to 1.26.7
- gstreamer1.0: upgrade to 1.26.7
- gstreamer1.0-libav: upgrade to 1.26.7
- gstreamer1.0-plugins-bad: upgrade to 1.26.7
- gstreamer1.0-plugins-base: upgrade to 1.26.7
- gstreamer1.0-plugins-good: upgrade to 1.26.7
- gstreamer1.0-plugins-ugly: upgrade to 1.26.7
- gstreamer1.0-python: upgrade to 1.26.7
- gstreamer1.0-rtsp-server: upgrade to 1.26.7
- gstreamer1.0-vaapi: upgrade to 1.26.7
- libarchive: upgrade to 3.8.3
- libarchive: upgrade to 3.8.4
- libpcap: upgrade to 1.10.6
- libpng: upgrade to 1.6.52
- libssh2: fix regression in KEX method validation (GH-1553)
- libxmlb: upgrade to 0.3.24
- linux-yocto/6.12: update to v6.12.60
- llvm/clang: Upgrade to 21.1.7
- mesa: upgrade to 25.2.8
- python3: upgrade to 3.13.11
- spdx30\_tasks: Fix *SPDX\_CUSTOM\_ANNOTATION\_VARS* implementation
- xserver-nodm-init: avoid race condition related to udev

## yocto-docs

- Add the sphinx-copybutton extension
- Fix bitbake version mapping for whinlatter
- Makefile: fix rsvg-convert --format capitalization
- brief-yoctoprojectqs/index.rst: fix improper code-block indentation
- brief-yoctoprojectqs/index.rst: switch shell block to to console/text blocks
- brief-yoctoprojectqs/index.rst: update available bitbake-setup configurations
- brief-yoctoprojectqs: specify what "recent Ubuntu Linux distribution" is
- dev-manual/limiting-resources.rst: update how to track pressure info
- make sure Quick Build section and System Requirements are in sync
- migration-guide: update 5.3 release notes download section
- migration-guides/release-notes-5.3.rst: add contributors
- migration-guides/release-notes-5.3.rst: add fixed cve
- migration-guides/release-notes-5.3.rst: add license updates
- migration-guides/release-notes-5.3.rst: add recipe upgrades
- migration-guides/release-notes-5.3.rst: latest changes from master
- overview-manual/concepts.rst: update the cross-development toolchain section
- poky.yaml.in: add DISTRO\_RELEASE\_SERIES
- ref-manual/classes.rst: document the image-container class
- ref-manual/faq.rst: add Q&A on third-party vuln scanning tools
- ref-manual/system-requirements.rst: add RockyLinux install instructions
- ref-manual/system-requirements.rst: fix AlmaLinux PDF build
- ref-manual/tasks.rst: document the do\_list\_image\_features task
- ref-manual/variables.rst: document WESTON\_USER/WESTON\_USER\_HOME variables
- ref-manual: Document *SPDX* 3.0.1 variables
- set\_versions.py: add wrynose as devbranch
- tools/build-docs-container: add CentOS Stream 9 support
- tools/build-docs-container: move container files in their own directory
- tools: add gen-cve-release-notes
- tools: ubuntu\_docs: remove duplicate python3-saneyaml

### Known Issues in Yocto-5.3.1

- N/A

### Contributors to Yocto-5.3.1

Thanks to the following people who contributed to this release:

- Alexander Kanavin
- Ankur Tyagi
- Antonin Godard
- Bruce Ashfield
- Chen Qi
- Deepesh Varatharajan
- Dmitry Baryshkov
- Gyorgy Sarvari
- Jayasurya Maganuru
- Jörg Sommer
- Lee Chee Yang
- Martin Jansa
- Mathieu Dubois-Briand
- Moritz Haase
- Paul Barker
- Peter Marko
- Quentin Schulz
- Robert Yang
- Stefano Tondo
- Vijay Anusuri
- Wang Mingyu
- Yash Shinde
- Yoann Congal
- Zhang Peng

## Repositories / Downloads for Yocto-5.3.1

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `whinlatter`
- Tag: `yocto-5.3.1`
- Git Revision: `102a33294e63a5581c413555040f790161fc80ff`
- Release Artefact: `yocto-docs-102a33294e63a5581c413555040f790161fc80ff`
- sha: `377b828c5dbf82b8a918360a52ff7b4122d37fd8d13d0451738edd57a1924083`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.1/yocto-docs-102a33294e63a5581c413555040f790161fc80ff.tar.bz2>  
  
<https://mirrors.kernel.org/yocto/yocto/yocto-5.3.1/yocto-docs-102a33294e63a5581c413555040f790161fc80ff.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `whinlatter`
- Tag: `yocto-5.3.1`
- Git Revision: `dd10706cfafb5574b7cf316fca2300d166ef71b0`
- Release Artefact: `oecore-dd10706cfafb5574b7cf316fca2300d166ef71b0`
- sha: `b3182231a4a10f57215289b0f42ebe658ee9b1ed0b0bfe414d846a778ff7c598`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.1/oecore-dd10706cfafb5574b7cf316fca2300d166ef71b0.tar.bz2>  
  
<https://mirrors.kernel.org/yocto/yocto/yocto-5.3.1/oecore-dd10706cfafb5574b7cf316fca2300d166ef71b0.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `whinlatter`
- Tag: `yocto-5.3.1`
- Git Revision: `6973ca663aaa9c3ab517ee960ab7985a5bf54c07`
- Release Artefact: `meta-yocto-6973ca663aaa9c3ab517ee960ab7985a5bf54c07`
- sha: `0e126b092e74bb217416d9603002b20db8e552b45b23d634cdae955fd089dfe2`



- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.1/meta-yocto-6973ca663aaa9c3ab517ee960ab7985a5bf54c07.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.3.1/meta-yocto-6973ca663aaa9c3ab517ee960ab7985a5bf54c07.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>

- Branch: `whinlatter`

- Tag: `yocto-5.3.1`

- Git Revision: `00323de97e397d4f6734ef2191806616989f5e10`

- Release Artefact: `meta-mingw-00323de97e397d4f6734ef2191806616989f5e10`

- sha: `c9a70539b12c0642596fde6a2766d4a6a8fec8b2a366453fb6473363127a1c77`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.1/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.3.1/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>

- Branch: `2.16`

- Tag: `yocto-5.3.1`

- Git Revision: `663021740bc086bd959a8457ad9ddb6da52a8278`

- Release Artefact: `bitbake-663021740bc086bd959a8457ad9ddb6da52a8278`

- sha: `a290072317e5c533fafd18608e61c9ebe9acf24d2ce46b43ba99df42c77e7073`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.1/bitbake-663021740bc086bd959a8457ad9ddb6da52a8278.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.3.1/bitbake-663021740bc086bd959a8457ad9ddb6da52a8278.tar.bz2>

## 17.4.4 Release notes for Yocto-5.3.2 (Whinlatter)

### Security Fixes in Yocto-5.3.2

- avahi: Fix CVE-2025-68276, CVE-2025-68468, CVE-2025-68471 and CVE-2026-24401
- curl: Fix CVE-2025-13034, CVE-2025-14017, CVE-2025-14524, CVE-2025-14819, CVE-2025-15079 and CVE-2025-15224

- dropbear: Fix CVE-2025-14282
- expat: Fix CVE-2026-24515 and CVE-2026-25210
- ffmpeg: Ignore CVE-2023-51791, CVE-2023-51793, CVE-2023-51794, CVE-2023-51795, CVE-2023-51796, CVE-2023-51797, CVE-2023-51798, CVE-2025-22921, CVE-2025-25468 and CVE-2025-25469
- glib-2.0: Fix CVE-2026-0988
- glibc: Fix CVE-2025-15281, CVE-2026-0861 and CVE-2026-0915
- gnupg: Fix CVE-2025-68973
- go: Fix CVE-2025-61730, CVE-2025-61731, CVE-2025-61728, CVE-2025-61726, CVE-2025-61732, CVE-2025-68119 and CVE-2025-68121
- grub: Fix CVE-2025-54770, CVE-2025-61661, CVE-2025-61662, CVE-2025-61663 and CVE-2025-61664
- inetutils: Fix CVE-2026-24061
- libarchive: Fix CVE-2025-60753
- libpng: Fix CVE-2026-22695 and CVE-2026-22801
- libsndfile1: Fix CVE-2025-56226
- libtasn1: Fix CVE-2025-13151
- libxml2: Fix CVE-2026-0989, CVE-2026-0990 and CVE-2026-0992
- linux-yocto/6.12: Ignore CVE-2021-47620, CVE-2022-48853, CVE-2022-48950, CVE-2022-50583, CVE-2022-50614, CVE-2022-50615, CVE-2022-50616, CVE-2022-50617, CVE-2022-50618, CVE-2022-50619, CVE-2022-50620, CVE-2022-50621, CVE-2022-50622, CVE-2022-50623, CVE-2022-50624, CVE-2022-50625, CVE-2022-50626, CVE-2022-50627, CVE-2022-50628, CVE-2022-50629, CVE-2022-50630, CVE-2022-50631, CVE-2022-50632, CVE-2022-50633, CVE-2022-50634, CVE-2022-50635, CVE-2022-50636, CVE-2022-50637, CVE-2022-50638, CVE-2022-50639, CVE-2022-50640, CVE-2022-50641, CVE-2022-50642, CVE-2022-50643, CVE-2022-50644, CVE-2022-50645, CVE-2022-50646, CVE-2022-50647, CVE-2022-50648, CVE-2022-50649, CVE-2022-50650, CVE-2022-50651, CVE-2022-50652, CVE-2022-50653, CVE-2022-50654, CVE-2022-50655, CVE-2022-50656, CVE-2022-50657, CVE-2022-50658, CVE-2022-50659, CVE-2022-50660, CVE-2022-50661, CVE-2022-50662, CVE-2022-50663, CVE-2022-50664, CVE-2022-50665, CVE-2022-50666, CVE-2022-50667, CVE-2022-50668, CVE-2022-50669, CVE-2022-50670, CVE-2022-50671, CVE-2022-50672, CVE-2022-50673, CVE-2022-50674, CVE-2022-50675, CVE-2022-50676, CVE-2022-50677, CVE-2022-50678, CVE-2022-50679, CVE-2022-50697, CVE-2022-50698, CVE-2022-50699, CVE-2022-50700, CVE-2022-50701, CVE-2022-50702, CVE-2022-50703, CVE-2022-50704, CVE-2022-50705, CVE-2022-50706, CVE-2022-50707, CVE-2022-50708, CVE-2022-50709, CVE-2022-50710, CVE-2022-50711, CVE-2022-50712, CVE-2022-50713, CVE-2022-50714, CVE-2022-50715, CVE-2022-50716, CVE-2022-50717, CVE-2022-50718, CVE-2022-50719, CVE-2022-50720, CVE-2022-50721, CVE-2022-50722, CVE-2022-50723, CVE-2022-50724, CVE-2022-50725, CVE-2022-50726, CVE-2022-50727, CVE-2022-50728, CVE-2022-50729, CVE-2022-50730, CVE-2022-50731, CVE-2022-50732, CVE-2022-50733, CVE-2022-50734, CVE-2022-50735, CVE-2022-50736, CVE-2022-50737, CVE-2022-50738, CVE-2022-50739, CVE-2022-50740, CVE-2022-50741, CVE-2022-50742, CVE-2022-50743, CVE-2022-50744, CVE-2022-50745, CVE-2022-50746, CVE-2022-50747, CVE-2022-50748, CVE-2022-50749, CVE-2022-50750, CVE-2022-50751,

## 17.4. Release 5.3 (whinlatter) 1155

[illegible]

CVE-2023-54259, CVE-2023-54260, CVE-2023-54261, CVE-2023-54262, CVE-2023-54263, CVE-2023-54264, CVE-2023-54265, CVE-2023-54266, CVE-2023-54267, CVE-2023-54268, CVE-2023-54269, CVE-2023-54270, CVE-2023-54271, CVE-2023-54272, CVE-2023-54273, CVE-2023-54274, CVE-2023-54275, CVE-2023-54276, CVE-2023-54277, CVE-2023-54278, CVE-2023-54279, CVE-2023-54280, CVE-2023-54281, CVE-2023-54282, CVE-2023-54283, CVE-2023-54284, CVE-2023-54285, CVE-2023-54286, CVE-2023-54287, CVE-2023-54288, CVE-2023-54289, CVE-2023-54291, CVE-2023-54292, CVE-2023-54293, CVE-2023-54294, CVE-2023-54295, CVE-2023-54296, CVE-2023-54297, CVE-2023-54298, CVE-2023-54299, CVE-2023-54300, CVE-2023-54301, CVE-2023-54302, CVE-2023-54303, CVE-2023-54304, CVE-2023-54305, CVE-2023-54306, CVE-2023-54307, CVE-2023-54308, CVE-2023-54309, CVE-2023-54310, CVE-2023-54311, CVE-2023-54312, CVE-2023-54313, CVE-2023-54314, CVE-2023-54315, CVE-2023-54316, CVE-2023-54317, CVE-2023-54318, CVE-2023-54319, CVE-2023-54320, CVE-2023-54321, CVE-2023-54322, CVE-2023-54323, CVE-2023-54324, CVE-2023-54325, CVE-2023-54326, CVE-2024-47683, CVE-2025-37884, CVE-2025-39745, CVE-2025-39822, CVE-2025-39905, CVE-2025-40210, CVE-2025-40214, CVE-2025-40216, CVE-2025-40218, CVE-2025-40219, CVE-2025-40220, CVE-2025-40221, CVE-2025-40222, CVE-2025-40223, CVE-2025-40224, CVE-2025-40225, CVE-2025-40226, CVE-2025-40227, CVE-2025-40228, CVE-2025-40229, CVE-2025-40230, CVE-2025-40231, CVE-2025-40232, CVE-2025-40233, CVE-2025-40234, CVE-2025-40235, CVE-2025-40236, CVE-2025-40237, CVE-2025-40238, CVE-2025-40239, CVE-2025-40240, CVE-2025-40241, CVE-2025-40242, CVE-2025-40243, CVE-2025-40244, CVE-2025-40245, CVE-2025-40246, CVE-2025-40248, CVE-2025-40249, CVE-2025-40250, CVE-2025-40251, CVE-2025-40252, CVE-2025-40253, CVE-2025-40254, CVE-2025-40255, CVE-2025-40256, CVE-2025-40257, CVE-2025-40258, CVE-2025-40259, CVE-2025-40260, CVE-2025-40261, CVE-2025-40262, CVE-2025-40263, CVE-2025-40264, CVE-2025-40265, CVE-2025-40266, CVE-2025-40267, CVE-2025-40268, CVE-2025-40269, CVE-2025-40270, CVE-2025-40271, CVE-2025-40272, CVE-2025-40273, CVE-2025-40274, CVE-2025-40275, CVE-2025-40277, CVE-2025-40278, CVE-2025-40279, CVE-2025-40280, CVE-2025-40281, CVE-2025-40282, CVE-2025-40283, CVE-2025-40284, CVE-2025-40285, CVE-2025-40286, CVE-2025-40287, CVE-2025-40288, CVE-2025-40289, CVE-2025-40290, CVE-2025-40291, CVE-2025-40292, CVE-2025-40293, CVE-2025-40294, CVE-2025-40295, CVE-2025-40296, CVE-2025-40297, CVE-2025-40298, CVE-2025-40299, CVE-2025-40301, CVE-2025-40302, CVE-2025-40303, CVE-2025-40304, CVE-2025-40305, CVE-2025-40306, CVE-2025-40307, CVE-2025-40308, CVE-2025-40309, CVE-2025-40310, CVE-2025-40311, CVE-2025-40312, CVE-2025-40313, CVE-2025-40314, CVE-2025-40315, CVE-2025-40316, CVE-2025-40317, CVE-2025-40318, CVE-2025-40319, CVE-2025-40320, CVE-2025-40321, CVE-2025-40322, CVE-2025-40323, CVE-2025-40324, CVE-2025-40326, CVE-2025-40327, CVE-2025-40328, CVE-2025-40329, CVE-2025-40330, CVE-2025-40331, CVE-2025-40332, CVE-2025-40333, CVE-2025-40334, CVE-2025-40335, CVE-2025-40336, CVE-2025-40337, CVE-2025-40339, CVE-2025-40340, CVE-2025-40341, CVE-2025-40342, CVE-2025-40343, CVE-2025-40344, CVE-2025-40346, CVE-2025-40347, CVE-2025-40348, CVE-2025-40349, CVE-2025-40350, CVE-2025-40351, CVE-2025-40352, CVE-2025-40353, CVE-2025-40354, CVE-2025-40356, CVE-2025-40357, CVE-2025-40358, CVE-2025-40359, CVE-2025-40360, CVE-2025-40362, CVE-2025-40363, CVE-2025-68167, CVE-2025-68168, CVE-2025-68169, CVE-2025-68170, CVE-2025-68171, CVE-2025-68172, CVE-2025-68173, CVE-2025-68176, CVE-2025-68177, CVE-2025-68178, CVE-2025-68179, CVE-2025-68180, CVE-2025-68181, CVE-2025-68182, CVE-2025-68183, CVE-2025-68184, CVE-2025-68185, CVE-2025-68186, CVE-2025-68187, CVE-2025-68188, CVE-2025-68189, CVE-2025-68190, CVE-2025-68191, CVE-2025-68192, CVE-2025-68194, CVE-2025-68196, CVE-2025-68197, CVE-2025-68198, CVE-2025-68199, CVE-2025-68200, CVE-2025-68201, CVE-2025-68202, CVE-2025-68204, CVE-2025-68205, CVE-2025-

68207, CVE-2025-68208, CVE-2025-68210, CVE-2025-68211, CVE-2025-68212, CVE-2025-68213, CVE-2025-68214, CVE-2025-68215, CVE-2025-68216, CVE-2025-68217, CVE-2025-68218, CVE-2025-68219, CVE-2025-68220, CVE-2025-68221, CVE-2025-68222, CVE-2025-68223, CVE-2025-68225, CVE-2025-68226, CVE-2025-68227, CVE-2025-68228, CVE-2025-68229, CVE-2025-68230, CVE-2025-68231, CVE-2025-68232, CVE-2025-68233, CVE-2025-68234, CVE-2025-68235, CVE-2025-68237, CVE-2025-68238, CVE-2025-68240, CVE-2025-68241, CVE-2025-68242, CVE-2025-68243, CVE-2025-68244, CVE-2025-68245, CVE-2025-68246, CVE-2025-68247, CVE-2025-68248, CVE-2025-68249, CVE-2025-68250, CVE-2025-68252, CVE-2025-68253, CVE-2025-68260, CVE-2025-68262, CVE-2025-68281, CVE-2025-68294, CVE-2025-68299, CVE-2025-68309, CVE-2025-68310, CVE-2025-68311, CVE-2025-68312, CVE-2025-68313, CVE-2025-68314, CVE-2025-68315, CVE-2025-68316, CVE-2025-68317, CVE-2025-68320, CVE-2025-68321, CVE-2025-68322, CVE-2025-68323, CVE-2025-68326, CVE-2025-68350, CVE-2025-68355, CVE-2025-68370, CVE-2025-68373, CVE-2025-68375, CVE-2025-68377, CVE-2025-68726, CVE-2025-68731, CVE-2025-68734, CVE-2025-68737, CVE-2025-68738, CVE-2025-68739, CVE-2025-68743, CVE-2025-68750, CVE-2025-68752, CVE-2025-68754, CVE-2025-68760, CVE-2025-68761, CVE-2025-68762, CVE-2025-68779, CVE-2025-68790, CVE-2025-68791, CVE-2025-68793, CVE-2025-68805, CVE-2025-68807, CVE-2025-68812, CVE-2025-71070, CVE-2025-71090, CVE-2025-71092, CVE-2025-71103, CVE-2025-71106, CVE-2025-71110, CVE-2025-71115, CVE-2025-71124, CVE-2025-71128, CVE-2025-71139, CVE-2025-71142, CVE-2025-71155, CVE-2025-71158, CVE-2025-71159, CVE-2025-71181, CVE-2025-71187, CVE-2026-22983, CVE-2026-22987, CVE-2026-22995, CVE-2026-23008, CVE-2026-23009, CVE-2026-23012, CVE-2026-23014, CVE-2026-23015, CVE-2026-23016, CVE-2026-23018, CVE-2026-23022, CVE-2026-23024, CVE-2026-23027, CVE-2026-23028, CVE-2026-23029, CVE-2026-23034, CVE-2026-23036, CVE-2026-23039, CVE-2026-23040, CVE-2026-23041, CVE-2026-23042, CVE-2026-23043, CVE-2026-23044, CVE-2026-23045, CVE-2026-23046, CVE-2026-23048, CVE-2026-23051, CVE-2026-23052, CVE-2026-23067, CVE-2026-23077, CVE-2026-23079, CVE-2026-23081, CVE-2026-23092, CVE-2026-23100, CVE-2026-23106 and CVE-2026-23109

- **linux-yocto/6.12:** Fix CVE-2024-58096, CVE-2024-58097, CVE-2025-22111, CVE-2025-38234, CVE-2025-38248, CVE-2025-38591, CVE-2025-39872, CVE-2025-40075, CVE-2025-40149, CVE-2025-40164, CVE-2025-40170, CVE-2025-40215, CVE-2025-40276, CVE-2025-40325, CVE-2025-40345, CVE-2025-68206, CVE-2025-68254, CVE-2025-68255, CVE-2025-68256, CVE-2025-68257, CVE-2025-68258, CVE-2025-68259, CVE-2025-68261, CVE-2025-68263, CVE-2025-68264, CVE-2025-68265, CVE-2025-68266, CVE-2025-68282, CVE-2025-68283, CVE-2025-68284, CVE-2025-68285, CVE-2025-68286, CVE-2025-68287, CVE-2025-68288, CVE-2025-68289, CVE-2025-68290, CVE-2025-68291, CVE-2025-68292, CVE-2025-68293, CVE-2025-68295, CVE-2025-68296, CVE-2025-68297, CVE-2025-68298, CVE-2025-68300, CVE-2025-68301, CVE-2025-68302, CVE-2025-68303, CVE-2025-68305, CVE-2025-68306, CVE-2025-68307, CVE-2025-68308, CVE-2025-68324, CVE-2025-68325, CVE-2025-68327, CVE-2025-68328, CVE-2025-68329, CVE-2025-68330, CVE-2025-68331, CVE-2025-68332, CVE-2025-68333, CVE-2025-68335, CVE-2025-68336, CVE-2025-68337, CVE-2025-68338, CVE-2025-68339, CVE-2025-68340, CVE-2025-68341, CVE-2025-68342, CVE-2025-68343, CVE-2025-68344, CVE-2025-68345, CVE-2025-68346, CVE-2025-68347, CVE-2025-68348, CVE-2025-68349, CVE-2025-68351, CVE-2025-68352, CVE-2025-68354, CVE-2025-68356, CVE-2025-68357, CVE-2025-68358, CVE-2025-68361, CVE-2025-68362, CVE-2025-68363, CVE-2025-68364, CVE-2025-68365, CVE-2025-68366, CVE-2025-68367, CVE-2025-68369, CVE-2025-68371, CVE-2025-68372, CVE-2025-68374, CVE-2025-68378, CVE-2025-68379, CVE-2025-68380, CVE-2025-68724, CVE-2025-68725,



## 17.4. Release 5.3 (whinlatter) 1159

23098, CVE-2026-23099, CVE-2026-23101, CVE-2026-23103, CVE-2026-23105, CVE-2026-23107, CVE-2026-23108 and CVE-2026-23110

- openssl: Fix CVE-2025-11187, CVE-2025-15467, CVE-2025-15468, CVE-2025-15469, CVE-2025-66199, CVE-2025-68160, CVE-2025-69418, CVE-2025-69419, CVE-2025-69420, CVE-2025-69421, CVE-2026-22795 and CVE-2026-22796
- python3-urllib3: Fix CVE-2026-21441
- util-linux: Fix CVE-2025-14104
- vim: ignore CVE-2025-66476
- webkitgtk: Fix CVE-2025-43343
- zlib: ignore CVE-2026-22184

## Fixes in Yocto-5.3.2

### bitbake

- bitbake-setup: ensure paths with timestamps in them are unique

### meta-yocto

- poky.conf: Bump version for 5.3.2 release

### openembedded-core

- build-appliance-image: Update to whinlatter head revisions
- devtool: deploy: Reset PATH after strip\_execs
- devtool: deploy: Run pseudo with correct PATH
- docbook-xml-dtd4: fix the fetching failure
- dpkg: Fix ADMINDIR
- expat: upgrade to 2.7.4
- ffmpeg: add a (possible) build race fix
- ffmpeg: fix a build race, hopefully for real this time
- glibc: stable 2.42 branch updates (912d89a766...)
- go: upgrade to 1.25.7
- libarchive: upgrade to 3.8.5
- libpng: upgrade to 1.6.54
- libtheora: set *CVE\_PRODUCT*
- linux-yocto/6.12: update to v6.12.69
- mobile-broadband-provider-info: upgrade to 20251101
- oeqa/gitarchive: Fix git push URL parameter



- oeqa/gitarchive: Push tag before copying log files
- oeqa/selftest/wic: test recursive dir copy on ext partitions
- openssl: upgrade to 3.5.5
- pseudo: Update to 1.9.3+git9ab513512d... (include an openat2 fix)
- scripts/install-buildtools: Update to 5.3.1
- scripts/oe-git-archive: Ensure new push parameter is specified
- selftest: devtool: Set PATH when running pseudo
- webkitgtk: upgrade to 2.50.4
- webkitgtk: workaround compile failure for large debug symbols
- wic/engine: fix copying directories into wic image with ext\* partition

### yocto-docs

- Add a new "Security" section
- Add a security manual
- Move security related manuals to the security manual
- README: remove obsolete poky repo references
- README: replace obsolete substitution variables
- Remove diagrams directory
- brief-yoctoprojectqs/index.rst: remove extra word from text
- bsp-guide/bsp.rst: remove obsolete poky repo references
- contributor-guide/identify-component.rst: remove obsolete poky repo references
- contributor-guide/recipe-style-guide.rst: explain difference between layer and recipe license(s)
- contributor-guide/submit-changes.rst: remove obsolete poky repo references
- dev-manual/build-quality.rst: remove obsolete poky repo references
- dev-manual/building.rst: remove obsolete poky repo references
- dev-manual/custom-distribution.rst: remove obsolete poky repo references
- dev-manual/custom-template-configuration-directory.rst: remove obsolete poky repo references
- dev-manual/debugging.rst: remove obsolete poky repo references
- dev-manual/error-reporting-tool.rst: remove obsolete poky repo references
- dev-manual/external-toolchain.rst: remove obsolete poky repo references
- dev-manual/init-manager.rst: remove obsolete poky repo references
- dev-manual/layers.rst: re-organize the document
- dev-manual/layers.rst: remove obsolete poky repo references

- dev-manual/libraries.rst: remove obsolete poky repo references
- dev-manual/licenses.rst: instruct to use git-archive instead of removing .git
- dev-manual/licenses.rst: remove obsolete poky repo references
- dev-manual/new-recipe.rst: remove obsolete poky repo references
- dev-manual/packages.rst: fix example recipe version
- dev-manual/packages.rst: pr server: fix and explain why r0.X increments on [SRCREV](#) change
- dev-manual/packages.rst: remove obsolete poky repo references
- dev-manual/packages.rst: rename r0.0 to r0 when [PR](#) server is not enabled
- dev-manual/poky-manual-setup.rst: mention the Source Directory
- dev-manual/poky-manual-setup.rst: remove obsolete poky repo references
- dev-manual/python-development-shell.rst: remove obsolete poky repo references
- dev-manual/qemu.rst: remove obsolete poky repo references
- dev-manual/qemu: add an example for the snapshot+nographic mode
- dev-manual/securing-images.rst: remove obsolete poky repo references
- dev-manual/start.rst: remove obsolete poky repo references
- dev-manual/temporary-source-code.rst: remove obsolete poky repo references
- dev-manual/upgrading-recipes.rst: move meta-openembedded to bitbake-builds/layers
- dev-manual/upgrading-recipes.rst: remove obsolete poky repo references
- dev-manual/vulnerabilities.rst: remove obsolete poky repo references
- dev-manual/wayland.rst: remove obsolete poky repo references
- dev-manual/wic.rst: remove obsolete poky repo references
- kernel-dev/advanced.rst: remove obsolete poky repo references
- kernel-dev/common.rst: remove obsolete poky repo references
- migration-guides/migration-1.4.rst: remove obsolete poky repo references
- migration-guides/migration-5.3.rst: add note on \*FLAGS behavior change
- migration-guides: add release notes for 4.0.32, 5.0.14, 5.0.15 and 5.3.1
- overview-manual/concepts.rst: remove obsolete poky repo references
- overview-manual/development-environment.rst: remove obsolete poky repo references
- overview-manual/yp-intro.rst: fix SDK type in bullet list
- overview-manual/yp-intro.rst: remove obsolete poky repo references
- overview-manual: convert YP-flow-diagram.png to SVG
- ref-manual/classes.rst: remove obsolete poky repo references

- ref-manual/devtool-reference.rst: remove obsolete poky repo references
- ref-manual/faq.rst: remove obsolete poky repo references
- ref-manual/features.rst: remove obsolete poky repo references
- ref-manual/images.rst: remove obsolete poky repo references
- ref-manual/release-process.rst: add a "Development Cycle" section
- ref-manual/release-process.rst: remove obsolete poky repo references
- ref-manual/release-process.rst: remove repeated "in the"
- ref-manual/structure.rst: remove obsolete poky repo references
- ref-manual/system-requirements.rst: fix wrong path to install-buildtools
- ref-manual/system-requirements.rst: remove obsolete poky repo references
- ref-manual/tasks.rst: remove obsolete poky repo references
- ref-manual/terms.rst: refresh the Build Directory definition
- ref-manual/terms.rst: refresh the OpenEmbedded build system definition
- ref-manual/terms.rst: refresh the OpenEmbedded-Core definition
- ref-manual/terms.rst: simplify the Source Directory definition
- ref-manual/variables.rst: document the `CCACHE_TOP_DIR` variable
- ref-manual/variables.rst: remove obsolete poky repo references
- ref-manual/yocto-project-supported-features.rst: remove obsolete poky repo reference
- sdk-manual/appendix-obtain.rst: remove obsolete poky repo references
- sdk-manual/intro.rst: remove obsolete poky repo references
- sdk-manual: appendix-customizing: use none lexer for BitBake code blocks
- sdk-manual: appendix-obtain: fix default path for eSDK installer script
- sdk-manual: appendix-obtain: replace directory structure PNG with a parsed-literal block
- sdk-manual: appendix-obtain: replace eSDK directory structure PNG with a parsed-literal block
- sdk-manual: appendix-obtain: use parsed-literal block for naming convention of the installer scripts
- sdk-manual: delete sdk-title PNG
- sdk-manual: fix improper indent of general form of tarball installer scripts
- sdk-manual: fix incorrect highlight language for console code-blocks
- sdk-manual: fix incorrect highlight language for text code-blocks
- sdk-manual: replace sdk-environment PNG with SVG
- sdk-manual: using: fix SDK filename example
- sdk-manual: working-projects: properly highlight code code-blocks

- security-manual/securing-images.rst: remove old links
- test-manual/ptest.rst: detail the exit code and output requirements
- test-manual/reproducible-builds.rst: remove obsolete poky repo references
- test-manual/runtime-testing.rst: remove obsolete poky repo references
- test-manual/understand-autobuilder.rst: remove obsolete poky repo references
- transitioning-to-a-custom-environment.rst: remove obsolete poky repo references
- tree-wide: figures: remove title PNGs
- what-i-wish-id-known.rst: remove obsolete poky repo references

### **Known Issues in Yocto-5.3.2**

- N/A

### **Contributors to Yocto-5.3.2**

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Aleksandar Nikolic
- Alexander Kanavin
- Amaury Couderc
- Ankur Tyagi
- Antonin Godard
- Bruce Ashfield
- Dragomir, Daniel
- Hongxu Jia
- Hugo SIMELIERE
- Jiaying Song
- Ken Kurematsu
- Khai Dang
- Lee Chee Yang
- Mark Hatle
- Mathieu Dubois-Briand
- Mohammad Rahimi
- Paul Barker
- Peter Marko
- Quentin Schulz

- Richard Purdie

## Repositories / Downloads for Yocto-5.3.2

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3.2](#)
- Git Revision: [9c363d270ab45f3443391fb7275817db69d8a5d4](#)
- Release Artefact: [yocto-docs-9c363d270ab45f3443391fb7275817db69d8a5d4](#)
- sha: [ca6638b5ab0cfc60c2f6e43db765fe0e87242c733e07ed6da55d01228067cf1f](#)
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.2/yocto-docs-9c363d270ab45f3443391fb7275817db69d8a5d4.tar.bz2>
  - <https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.2/yocto-docs-9c363d270ab45f3443391fb7275817db69d8a5d4.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3.2](#)
- Git Revision: [21314665e198c1abe458d0bad5c4d14d4c3ad856](#)
- Release Artefact: [oecore-21314665e198c1abe458d0bad5c4d14d4c3ad856](#)
- sha: [9ccfb0e279ccd1c683de2ed04db2f2b3acb81d9d50b7cbc0484fd2c1bc379a1e](#)
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.2/oecore-21314665e198c1abe458d0bad5c4d14d4c3ad856.tar.bz2>
  - <https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.2/oecore-21314665e198c1abe458d0bad5c4d14d4c3ad856.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3.2](#)
- Git Revision: [691ff0fbeb54eceb26d90140d7a8f672532235b](#)
- Release Artefact: [meta-yocto-691ff0fbeb54eceb26d90140d7a8f672532235b](#)
- sha: [3ef0e1c99820e15eeda97c16579173f7818ea84964bc73a1859827d836be6405](#)

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.2/meta-yocto-691ff0fbeab54eceb26d90140d7a8f672532235b.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.2/meta-yocto-691ff0fbeab54eceb26d90140d7a8f672532235b.tar.bz2>

### meta-qcom

- Repository Location: <https://git.yoctoproject.org/meta-qcom>

- Branch: `whinlatter`

- Tag: `yocto-5.3.2`

- Git Revision: `49bc2113adb0b86d463c311d32d4fb1007fe4845`

- Release Artefact: `meta-qcom-49bc2113adb0b86d463c311d32d4fb1007fe4845`

- sha: `ccd82e54bfe30786cd0792175cb9b6b74c98d613ff42832036bcaa6e96582683`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.2/meta-qcom-49bc2113adb0b86d463c311d32d4fb1007fe4845.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.2/meta-qcom-49bc2113adb0b86d463c311d32d4fb1007fe4845.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>

- Branch: `whinlatter`

- Tag: `yocto-5.3.2`

- Git Revision: `00323de97e397d4f6734ef2191806616989f5e10`

- Release Artefact: `meta-mingw-00323de97e397d4f6734ef2191806616989f5e10`

- sha: `c9a70539b12c0642596fde6a2766d4a6a8fec8b2a366453fb6473363127a1c77`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.2/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.2/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>

- Branch: `2.16`

- Tag: `yocto-5.3.2`

- Git Revision: `7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0`

- Release Artefact: `bitbake-7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0`
- sha: `06dd68908a5ffafae46ff7616e93a80f8b73c016f541e9517cf63b05f52f15c7`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.2/bitbake-7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.2/bitbake-7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0.tar.bz2>

## 17.4.5 Release notes for Yocto-5.3.3 (Whinlatter)

### Security Fixes in Yocto-5.3.3

- alsa-lib: patch CVE-2026-25068
- busybox: Fix CVE-2025-60876
- ffmpeg: Ignore CVE-2025-12343
- freetype: Fix CVE-2026-23865
- gdk-pixbuf: Fix CVE-2025-6199
- glib-2.0: Fix CVE-2026-1484, CVE-2026-1485 and CVE-2026-1489
- gnutls: Fix CVE-2025-14831
- go: Fix CVE-2026-25679, CVE-2026-27137, CVE-2026-27138, CVE-2026-27139 and CVE-2026-27142
- harfbuzz: Fix CVE-2026-22693
- inetutils: Fix CVE-2026-28372
- libpam: Ignore CVE-2024-10041
- libpng: Fix CVE-2026-25646
- linux-yocto: Ignore CVE-2022-38096, CVE-2023-6535, CVE-2023-39176, CVE-2023-39179 and CVE-2023-39180
- python3-pip: Fix CVE-2026-1703
- python3-urllib3: Fix CVE-2025-66471
- zlib: Fix CVE-2026-27171

### Fixes in Yocto-5.3.3

#### meta-yocto

- poky.conf: Bump version for 5.3.3 release

## openembedded-core

- README: Add whinlatter subject-prefix to git-send-email suggestion
- avahi: Remove a reference to the rejected [CVE-2021-36217](#)
- b4-config: add send-prefixes for whinlatter
- build-appliance-image: Update to whinlatter head revisions
- classes/buildhistory: Do not sign buildhistory commits
- create-pull-request: Keep commit hash to be pulled in cover email
- glib-2.0: upgrade to 2.86.4
- gnutls: fix postinst script for \${PN}-fips for multilibs
- gnutls: use libtool to install test binaries
- go: upgrade to 1.25.8
- libpng: upgrade to 1.6.55
- linux-yocto: apply cve-exclusions also to rt and tiny recipe variants
- lsb.py: strip ' from os-release file
- lz4: Remove a reference to the rejected [CVE-2025-62813](#)
- pseudo: Update to include a fix for systems with kernel <5.6
- python3: skip flaky test\_default\_timeout test
- scripts/install-buildtools: Update to 5.3.2
- wic/engine: error on old host debugfs for standalone directory copy
- wireless-regdb: upgrade to 2026.02.04

## yocto-docs

- Makefile: pass -silent to latexmk
- dev-manual: delete references to "tar" package format
- overview-manual/concepts: list other possible class directories
- overview-manual: escape wildcard in inline markup
- qemu.rst: parsing of the code-block was not done
- ref-manual/classes.rst: fix broken links to U-Boot documentation
- tools/host\_packages\_scripts/tlmgr\_docs\_pdf.sh: install perl
- what-i-wish-id-known.rst: replace figure by the new SVG



### Known Issues in Yocto-5.3.3

- N/A

### Contributors to Yocto-5.3.3

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Ankur Tyagi
- Antonin Godard
- Benjamin Robin (Schneider Electric)
- Daniel Dragomir
- Fabio Berton
- Hugo SIMELIERE
- Jan Vermaete
- Kristiyan Chakarov
- Liu Yiding
- Livin Sunny
- Martin Jansa
- Michael Opdenacker
- Paul Barker
- Peter Marko
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Ross Burton
- Shaik Moin
- Vijay Anusuri
- Yoann Congal

### Repositories / Downloads for Yocto-5.3.3

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3.3](#)
- Git Revision: [82bd1a71e6e6a707d0009725969976cf2256af36](#)

- Release Artefact: [yocto-docs-82bd1a71e6e6a707d0009725969976cf2256af36](#)
- sha: [fcf7020e34198f3b89077f9649cec579f4d23228f7f0a3a28a21c6b5b3649857](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.3/yocto-docs-82bd1a71e6e6a707d0009725969976cf2256af36.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.3/yocto-docs-82bd1a71e6e6a707d0009725969976cf2256af36.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3.3](#)
- Git Revision: [ab57471acad7ce2a037480dc7b301104620f1ebf](#)
- Release Artefact: [oecore-ab57471acad7ce2a037480dc7b301104620f1ebf](#)
- sha: [63ed486722e186d517e333c204def0a7bf578ca78bdeb2ad982625c49e7ee833](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.3/oecore-ab57471acad7ce2a037480dc7b301104620f1ebf.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.3/oecore-ab57471acad7ce2a037480dc7b301104620f1ebf.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: [whinlatter](#)
- Tag: [yocto-5.3.3](#)
- Git Revision: [9b98ec5e6cfb6c9dc74d3c2e6304eeb274f7c487](#)
- Release Artefact: [meta-yocto-9b98ec5e6cfb6c9dc74d3c2e6304eeb274f7c487](#)
- sha: [fcb81c6835036c4157b16dfc9f6d8c5a7dd0ed7ac72f59be238e99b486b1f8fa](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.3/meta-yocto-9b98ec5e6cfb6c9dc74d3c2e6304eeb274f7c487.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.3/meta-yocto-9b98ec5e6cfb6c9dc74d3c2e6304eeb274f7c487.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [whinlatter](#)

- Tag: `yocto-5.3.3`
- Git Revision: `00323de97e397d4f6734ef2191806616989f5e10`
- Release Artefact: `meta-mingw-00323de97e397d4f6734ef2191806616989f5e10`
- sha: `c9a70539b12c0642596fde6a2766d4a6a8fec8b2a366453fb6473363127a1c77`
- Download Locations:  
  
`https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.3/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2`  
  
`https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.3/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2`

#### bitbake

- Repository Location: `https://git.openembedded.org/bitbake`
- Branch: `2.16`
- Tag: `yocto-5.3.3`
- Git Revision: `7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0`
- Release Artefact: `bitbake-7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0`
- sha: `06dd68908a5ffafae46ff7616e93a80f8b73c016f541e9517cf63b05f52f15c7`
- Download Locations:  
  
`https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.3/bitbake-7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0.tar.bz2`  
  
`https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.3/bitbake-7af7e04f3adc8ba144d9e2e6b37ed4ddb3b59df0.tar.bz2`

## 17.4.6 Release notes for Yocto-5.3.4 (Whinlatter)

### Security Fixes in Yocto-5.3.4

- binutils: Fix CVE-2025-69644, CVE-2025-69647, CVE-2025-69648, CVE-2025-69649 and CVE-2025-69652
- binutils: Ignore CVE-2025-69650 and CVE-2025-69651
- curl: Fix CVE-2026-1965, CVE-2026-3783, CVE-2026-3784 and CVE-2026-3805
- expat: Fix CVE-2026-32776, CVE-2026-32777 and CVE-2026-32778
- glibc: Fix CVE-2026-4437 and CVE-2026-4438
- go: Fix CVE-2026-27140, CVE-2026-27143, CVE-2026-27144, CVE-2026-32280, CVE-2026-32281, CVE-2026-32282, CVE-2026-32283, CVE-2026-32288 and CVE-2026-32289
- inetutils: Fix CVE-2026-32746
- libpng: Fix CVE-2026-33416 and CVE-2026-33636

- libsoup: fix [CVE-2025-32049](#) and [CVE-2026-1539](#)
- nfs-utils: Fix [CVE-2025-12801](#)
- openssl: Fix [CVE-2026-2673](#), [CVE-2026-28387](#), [CVE-2026-28388](#), [CVE-2026-28389](#), [CVE-2026-28390](#), [CVE-2026-31789](#) and [CVE-2026-31790](#)
- python3-pyopenssl: Fix [CVE-2026-27448](#) and [CVE-2026-27459](#)
- python3: Fix [CVE-2025-15282](#)
- sqlite3: Fix [CVE-2025-70873](#)
- vim: Fix [CVE-2026-25749](#), [CVE-2026-26269](#), [CVE-2026-28418](#), [CVE-2026-28419](#) and [CVE-2026-33412](#)

## Fixes in Yocto-5.3.4

### bitbake

- runqueue.py: make sure we use bb multiprocessing
- tests/fetch: Avoid using git protocol in tests

### meta-yocto

- poky.conf: Bump version for 5.3.4 release
- poky: Fix CentOS Stream 9 distro name

### openembedded-core

- archiver: Don't try to preserve all attributes when copying files
- barebox/barebox-tools: upgrade to 2025.09.3
- binutils: Fix build with GLIBC 2.43 on the host
- binutils: Upgrade to 2.45.1 release
- build-appliance-image: switch [SRC\\_URI](#) to https protocol
- build-appliance-image: Update to whinlatter head revisions
- ca-certificates: upgrade to 20260223
- ccache: upgrade to 4.12.3
- dtc: backport fix for build with glibc-2.43
- gcc: backport a fix for building with gcc-16
- gettext: backport gnulib changes to fix build with glibc-2.43 on host
- glibc: stable 2.42 branch updates ([a56a2943d2c...](#))
- go: upgrade to 1.25.9
- libarchive: upgrade to 3.8.6
- libpng: upgrade to 1.6.56

- libsoup: upgrade to 3.6.6
- libxcrypt: avoid discarded-qualifiers build failure with glibc 2.43
- libxcrypt: Fix build wrt C23 support
- libxcrypt: Use configure knob to disable warnings as errors
- libxmlb: upgrade to 0.3.25
- license.py: Drop visit\_Str from SeenVisitor in selftest
- m4: backport 3 gnulib changes to fix build with glibc-2.43 on host
- meta/files/layers.example.json: switch to https clone URIs
- oe-setup-build: *TEMPLATECONF* were not applied correctly
- oeqa/sdk: Default to https git protocol for YP/OE repos
- oeqa/selftest/devtool: add vulkan feature check for test needing it
- oeqa/selftest/git-submodule-test: Default to https git protocol for YP/OE repos
- oeqa/selftest: add wayland feature check for tests needing it
- openssl: upgrade to 3.5.6
- ovmf: backport a fix for build with gcc-16
- pseudo: Add fix for glibc 2.43
- ptest-runner: Upgrade to 2.5.1
- ptest-runner: Use git tag in *SRC\_URI*
- python3-pip: drop unused Windows distlib launcher templates
- python3-setuptools: drop Windows launcher executables on non-mingw builds
- python3: Fix test under ptest-runner 2.5.1
- python3: upgrade to 3.13.12
- recipetool: Recognise <https://git>. as git urls
- report-error.bbclass: replace 'codecs.open()' with 'open()'
- scripts/install-buildtools: Update to 5.3.3
- scripts: Default to https git protocol for YP/OE repos
- selftest/gdbserver: replace shutil.unpack\_archive with tarfile extract
- selftest/minidebuginfo: extract files from tar archive using tarfile module
- selftest/scripts: Update old git protocol references
- spirv-tools: backport a fix for building with gcc-16
- systemd: backport fix to build with glibc-2.43 on host
- tzdata/tzcode-native: upgrade to 2026a

- util-linux: backport fix to build with glibc-2.43 on host
- virglrenderer: Fix build with glibc 2.43+
- yocto-uninative: Update to 5.1 for glibc 2.43

### yocto-docs

- contributor-guide/submit-changes.rst: Added missing word
- dev-manual/new-recipe.rst: rework Unpacking Code section
- migration-guide: add release notes for 4.0.33 4.0.34 5.0.16 5.0.17 5.3.2 5.3.3
- sphinx-static/theme\_overrides.css: switch to a fixed width documentation

### Known Issues in Yocto-5.3.4

- N/A

### Contributors to Yocto-5.3.4

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Alexander Kanavin
- Andrej Kozemcak
- Anil Dongare
- Ankur Tyagi
- Antonin Godard
- Changqing Li
- Deepak Rathore
- Hemanth Kumar M D
- Hitendra Prajapati
- Jinfeng Wang
- Khem Raj
- Krupal Ka Patel
- Lee Chee Yang
- Logan Gallois
- Martin Jansa
- Michael Halstead
- Paul Barker
- Peter Marko

- Richard Purdie
- Sunil Dora
- Trevor Gamblin
- Vijay Anusuri
- Wang Mingyu
- Yanis BINARD
- Yoann Congal
- Zoltán Böszörményi

## Repositories / Downloads for Yocto-5.3.4

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `whinlatter`
- Tag: `yocto-5.3.4`
- Git Revision: `10818445a22c524de0934901547cf676256c2b9d`
- Release Artefact: `yocto-docs-10818445a22c524de0934901547cf676256c2b9d`
- sha: `f9e0b155730ba23b83febd40b6e5d6e22c624d083cccb569cfff4a83ef3fde43`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.4/yocto-docs-10818445a22c524de0934901547cf676256c2b9d.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.4/yocto-docs-10818445a22c524de0934901547cf676256c2b9d.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `whinlatter`
- Tag: `yocto-5.3.4`
- Git Revision: `8751ec83421192fc0f8495fb95798f9eb7be77a0`
- Release Artefact: `oecore-8751ec83421192fc0f8495fb95798f9eb7be77a0`
- sha: `d587dc39a046a1a48f4cd33f5e9dd79b7d0948d71a9151fcf5542641893be229`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.4/oecore-8751ec83421192fc0f8495fb95798f9eb7be77a0.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.4/oecore-8751ec83421192fc0f8495fb95798f9eb7be77a0.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `whinlatter`
- Tag: `yocto-5.3.4`
- Git Revision: `3f2e6b6fadfa542f0fe3738375a2f9fcbd4c1f6e`
- Release Artefact: `meta-yocto-3f2e6b6fadfa542f0fe3738375a2f9fcbd4c1f6e`
- sha: `b942dc726a631b52284d4fe62dda4b97d880fea758a7090a8590cca964865e30`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.4/meta-yocto-3f2e6b6fadfa542f0fe3738375a2f9fcbd4c1f6e.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.4/meta-yocto-3f2e6b6fadfa542f0fe3738375a2f9fcbd4c1f6e.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `whinlatter`
- Tag: `yocto-5.3.4`
- Git Revision: `00323de97e397d4f6734ef2191806616989f5e10`
- Release Artefact: `meta-mingw-00323de97e397d4f6734ef2191806616989f5e10`
- sha: `c9a70539b12c0642596fde6a2766d4a6a8fec8b2a366453fb6473363127a1c77`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.4/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.4/meta-mingw-00323de97e397d4f6734ef2191806616989f5e10.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.16`
- Tag: `yocto-5.3.4`
- Git Revision: `713fbdbb9ecc195ceb2216a2345e0d79dbec2135`
- Release Artefact: `bitbake-713fbdbb9ecc195ceb2216a2345e0d79dbec2135`
- sha: `1d0f14e8bc71a39de4207aeeb329cb1d2541089c07e954131bf37a3d1b66b823`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.3.4/bitbake-713fbdbb9ecc195ceb2216a2345e0d79dbec2135.tar.bz2>



<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.3.4/bitbake-713fbdb9ecc195ceb2216a2345e0d79dbec2135.tar.bz2>

## 17.5 Release 5.2 (walnascar)

### 17.5.1 Release 5.2 (walnascar)

#### Migration notes for 5.2 (walnascar)

This section provides migration information for moving to the Yocto Project 5.2 Release (codename "walnascar") from the prior release.

#### **debug-tweaks removed from *IMAGE\_FEATURES***

The `debug-tweaks` image feature is now removed because it was too vague about what it achieved: an image on which the `root` user can login without a password.

To achieve the same result, the features previously added by `debug-tweaks` should be manually added to the *IMAGE\_FEATURES* variable. These are:

- `allow-empty-password`
- `allow-root-login`
- `empty-root-password`
- `post-install-logging`

Such a statement would be:

```
IMAGE_FEATURES += "allow-empty-password allow-root-login empty-root-password post-  
↪install-logging"
```

See the list of available image features in the *Image Features* section of the Yocto Project Reference Manual.

#### Supported kernel versions

The *OLDEST\_KERNEL* setting is 5.15 in this release, meaning that out the box, older kernels are not supported. See *4.3 migration notes* for details.

#### Supported distributions

Compared to the previous releases, running BitBake is supported on new GNU/Linux distributions:

- Fedora 41
- CentOS Stream 9

On the other hand, some earlier distributions are no longer supported:

- CentOS Stream 8
- Fedora 38

- OpenSUSE Leap 15.4
- Ubuntu 20.04

See *all supported distributions*.

## Rust language changes

- Recipes inheriting the *cargo* do not install libraries by default anymore. This behavior can be controlled by the *CARGO\_INSTALL\_LIBRARIES* variable.

## systemd changes

- Support for *split-usr* and *unmerged-usr* are now removed after Systemd was updated to version 255. This option allowed installing Systemd in a system where directories such as */lib*, */sbin* or */bin* are *not* merged into */usr*.

As a consequence, the *systemd* recipe no longer contains the *usrmerge PACKAGECONFIG* option as it is now implied by default.

- *systemd.bbclass*: If a *systemd* service file had referred to other service files by starting them via *Also*, the other service files were automatically added to the *FILES* variable of the same package. Example:

*a.service* contains:

```
[Install]
Also=b.service
```

If *a.service* is packaged in package A, *b.service* was automatically packaged into package A as well. This happened even if *b.service* was explicitly added to package B using *FILES* and *SYSTEMD\_SERVICE* variables. This prevented such services from being packaged into different packages. Therefore, this automatic behavior has been removed for service files (but not for socket files). Now all service files must be explicitly added to *FILES*.

- Add *create-log-dirs* back to the configuration options. To enable persistent logging a user can now set the "Storage" option of *journald.conf* to "persistent". The */var/log/journal* directory is now used for logging instead of */run/log*.
- If *pni-names* is not in the *DISTRO\_FEATURES*, the *Predictable Network Interface names* systemd feature will now be disabled. Previously the feature was still enabled even if *pni-names* was not part of *DISTRO\_FEATURES*. Make sure to add the feature to *DISTRO\_FEATURES* if you want to keep this systemd behavior.

## Multiconfig changes

The value of *BB\_CURRENT\_MC* was changed from *default* to an empty string for the default multiconfig configuration to avoid needing to map the values within BitBake. This was already not happening in some cases so this fixes some obscure bugs.

Any logic based on *BB\_CURRENT\_MC* equalling to *default* by default should be changed to be equal to an empty string.

## Virtual toolchain provider changes

Support was added for virtual providers on a per-recipe basis for specific key toolchain providers listed in `BB_VIRTUAL_RECIPE_PROVIDERS`. As part of that support, the `cross` providers were simplified to remove the triplet prefix (*`TARGET_PREFIX`*, *`SDK_PREFIX`* and *`HOST_PREFIX`*) and generalise the naming. Here are examples of how references to these variables can be changed to use the new `cross` syntax:

```
virtual/${HOST_PREFIX}binutils -> virtual/cross-binutils
virtual/${TARGET_PREFIX}binutils -> virtual/cross-binutils

virtual/${HOST_PREFIX}gcc -> virtual/cross-cc
virtual/${TARGET_PREFIX}gcc -> virtual/cross-cc
virtual/${SDK_PREFIX}gcc -> virtual/nativesdk-cross-cc

virtual/${HOST_PREFIX}compilerlibs -> virtual/compilerlibs
virtual/${TARGET_PREFIX}compilerlibs -> virtual/compilerlibs
virtual/nativesdk-${SDK_PREFIX}compilerlibs -> virtual/nativesdk-compilerlibs

virtual/${TARGET_PREFIX}g++ -> virtual/cross-c++
```

A ***PREFERRED\_PROVIDER*** assignment can be transformed as follows:

```
PREFERRED_PROVIDER_virtual/${TARGET_PREFIX}binutils -> PREFERRED_PROVIDER_virtual/
↪cross-binutils
PREFERRED_PROVIDER_virtual/${SDK_PREFIX}binutils -> PREFERRED_PROVIDER_virtual/
↪cross-binutils:class-nativesdk
PREFERRED_PROVIDER_virtual/${SDK_PREFIX}g++ -> PREFERRED_PROVIDER_virtual/
↪nativesdk-cross-c++
```

The above examples should cover most cases, but there might be situations where replacing is not as straightforward. For more examples, see the commit "[classes/recipes: Switch virtual/XXX-gcc to virtual/cross-cc \(and c++/binutils\)](#)" in *OpenEmbedded-Core (OE-Core)*.

## autotools\* changes

- Changes to how `aclocal` is invoked means that `ACLOCALDIR` and `ACLOCAL_EXTRAPATH` are no longer used.
- Directories containing `m4` files are no longer found automatically and passed to `autoreconf`. If a recipe fails to configure because it cannot find `m4` macros, then usually the solution is to set `EXTRA_AUTORECONF += "-I path/to/m4"` in the recipe.
- The ***autotools\**** class now requires any recipe that inherits the class to have a `configure` script. The configuration script location is stored in the ***CONFIGURE\_SCRIPT*** variable. The ***do\_configure*** task will fail if the script is missing.

### UBOOT\_ENTRYPOINT changes

The `UBOOT_ENTRYPOINT` variable should now be defined with a leading `0x` to its value. For example, consider the following assignment:

```
UBOOT_ENTRYPOINT ?= "20008000"
```

This should now be replaced by:

```
UBOOT_ENTRYPOINT ?= "0x20008000"
```

### Git fetcher: support for multiple revisions per URL removed

The support for having multiple Git revisions per URL in `SRC_URI` was removed from BitBake, which means the following syntax is not supported anymore:

```
SRC_URI = "git://some.host/somepath;bareclone=1;branch=branchX,branchY;name=nameX,
↪nameY"
SRCREV_nameX = "xxxxxxxxxxxxxxxxxxxxxxxx"
SRCREV_nameY = "yyyyyyyyyyyyyyyyyyyyyy"
```

This was rarely used in the core repositories because it would only ever make sense for bare clones (the `bareclone=1` `SRC_URI` option) where recipes take care of the Git checkout. This removal simplifies the code logic in several places.

If one of your recipes is using this mechanism, you can split the code source fetching into two separate entries:

```
SRC_URI = "git://some.host/somepath;bareclone=1;branch=branchX;name=nameX \
          git://some.host/somepath;bareclone=1;branch=branchY;name=nameY"
SRCREV_nameX = "xxxxxxxxxxxxxxxxxxxxxxxx"
SRCREV_nameY = "yyyyyyyyyyyyyyyyyyyyyy"
```

### Git fetcher: Branch parameter now required in `SRC_URI`

The `branch` parameter is now required when specifying a Git repository in `SRC_URI`, for example:

```
SRC_URI = "git://some.host/somepath;branch=branchX"
```

A missing `branch` parameter used to produce a warning, and will now produce an error.

### Recipe changes

- The `libnss-mdns` recipe is now renamed to `avahi-libnss-mdns` to avoid a conflict with meta-networking.
- `ptest` support for the `valgrind` recipe was removed, due to regressions occurring after updating Glibc to 2.41.

## Removed variables

The following variables have been removed:

- `PACKAGE_SNAP_LIB_SYMLINKS`: related to an unmaintained and obsolete "micro" *distro*.
- `SETUPTOOLS_INSTALL_ARGS`: obsolete and unused variable.
- `BB_DANGLINGAPPENDS_WARNONLY`: support for only warning the user when a `.bbappend` file doesn't apply to the original recipe has been dropped. See the *Appending Other Layers Metadata With Your Layer* section of the Yocto Project Development Tasks Manual for alternatives to this variable.

## Removed recipes

The following recipes have been removed in this release:

- `liburi-perl`: moved to `meta-perl`.
- `python3-isodate`: moved to `meta-python`.
- `python3-iniparse`: removed as there are no consumers of this recipe in `openembedded-core` or `meta-openembedded`.
- `blktool`: It was created in 2004 as an alternative to `hdparm` and never updated since (while `hdparm` remains active).
- `cargo-c-native`: converted to a target recipe and renamed to `cargo-c`.
- `libnss-mdns`: renamed to `avahi-libnss-mdns`

## Removed classes

The following classes have been removed in this release:

- `migrate_localcount.bbclass`: obsolete class for which code was already removed in 2012.

## Removed features

- The `ld-is-gold` distro feature was removed from the *`DISTRO_FEATURES`*.

## Miscellaneous changes

- *`ZSTD_COMPRESSION_LEVEL`* is now a plain integer number instead of a dash-prefixed command-line option (e.g. it should be set to 3 rather than -3).
- Until now, the variable *`UBOOT_ENV`* was processed both by the U-Boot recipe and by the `kernel-fitimage.bbclass`. However, adding a U-Boot script to the kernel FIT image is a different and independent thing, which also requires an independent variable. Therefore, the *`UBOOT_ENV`* is no longer handled by the `kernel-fitimage.bbclass`. There is a new variable *`FIT_UBOOT_ENV`* which should be used for adding a U-Boot script to a FIT image.
- The `devtool ide-sdk` utility has been removed from the *`eSDK`* (but remains available in the BitBake environment).

## 17.5.2 Release notes for 5.2 (walnascar)

### New Features / Enhancements in 5.2

- Linux kernel 6.12, gcc 14.2, glibc 2.41, LLVM 19.1.7, and over 300 other recipe upgrades.
- Minimum Python version required on the host: 3.9.
- New variables:
  - `linux-firmware`: Add the `FIRMWARE_COMPRESSION` variable which allows compression the firmwares provided by the `linux-firmware` recipe. Possible values are `xz` and `zst`.
  - Reproducibility: Add the `OEQA_REPRODUCIBLE_TEST_LEAF_TARGETS` variable which enables a reproducibility test on recipes using *Shared State* for the dependencies. See *Reproducible Builds*.
  - `systemd`: Add `WATCHDOG_RUNTIME_SEC`: for controlling the `RuntimeWatchdogSec` option in `/etc/systemd/system.conf`.
  - `FIT_UBOOT_ENV` to allow including a u-boot script as a text in a fit image. See the `kernel-fitimage` for more information.
  - `meson`: `MESON_INSTALL_TAGS` to allow passing install tags (`--tags`) to the `meson install` command during the `do_install` task.
  - `cve-check`: `NVD_DB_VERSION` to allow choosing the CVE feed when using the `cve-check` class.
  - The `BB_USE_HOME_NPMRC` controls whether or not BitBake uses the user's `.npmrc` file within their home directory within the npm fetcher. This can be used for authentication of private NPM registries, among other uses.
  - The `GRUB_MKIMAGE_OPTS` can be used to control the flags to the `grub-mkimage` command in the context of the GRUB recipe (`grub-efi`).
  - The `SPDX_PACKAGE_VERSION` variable controls the package version as seen in the SPDX 3.0 JSON output (`software_packageVersion`).
- Kernel-related changes:
  - `cml1`: in `do_diffconfig`, do not override `.config` with `.config.orig`. This applies to other recipes using the class `cml1`.
  - `linux-firmware`: add following new firmware packages:
    - \* `qcom-qcm6490-audio`
    - \* `qcom-qcm6490-compute`
    - \* `qcom-adreno-a663`
    - \* `qcom-qcm6490-adreno`
    - \* `qcom-sa8775p-adreno`
    - \* `qcom-qcm6490-ipa`
    - \* `qcom-x1e80100-audio`
    - \* `qcom-qcs615-adreno`

- \* qcom-aic100
  - \* qcom-qdu100
  - \* qca-qca2066
  - \* qca-qca61x4-serial
  - \* qca-qca61x4-usb
  - \* qca-qca6390
  - \* qca-qca6698
  - \* qca-wcn3950
  - \* qca-wcn3988
  - \* qca-wcn399x
  - \* qca-wcn6750
  - \* qca-wcn7850
  - \* qcom-2-license
  - \* qcom-aic100
  - \* qcom-qcm6490-wifi
  - \* qcom-qdu100
  - \* qcom-sa8775p-audio
  - \* qcom-sa8775p-compute
  - \* qcom-sa8775p-generalpurpose
  - \* qcom-x1e80100-lenovo-t14s-g6-adreno
  - \* qcom-x1e80100-lenovo-t14s-g6-audio
  - \* qcom-x1e80100-lenovo-t14s-g6-compute
  - \* qcom-adreno-a623
  - \* qcom-qcs8300-adreno
  - \* qca-qca2066
  - \* qcom-adreno-a2xx
- linux-firmware: split amgpu, ath10k, ath11k and ath12k in separate packages.
  - The *kernel-yocto* classes now supports in-tree configuration fragments. These can be added with the *KERNEL\_FEATURES* variable.
  - Kernel configuration audit can now be disabled by setting *KMETA\_AUDIT* to 1.
  - The *kern-tools* recipe is now able to recognize files ending with *.config* for *kernel-yocto*-based Kernel recipes.

- Support the LZMA compression algorithm in the *kernel-uboot* class. This can be done by setting the variable *FIT\_KERNEL\_COMP\_ALG* to *lzma*.
- *kernel-yocto*: Reproducibility for commits created by the *kernel-yocto* class was improved.
- *kernel-arch*: add *-fmacro-prefix-map* in *KERNEL\_CC* to fix a reproducibility issue.
- New core recipes:
  - *python3-pefile*: required for the *uki* class.
  - Add initial support for the *Barebox* bootloader, along with associated OEQA test cases. This adds the *barebox* and the *barebox-tools* recipes.
  - Import *makedumpfile* from *meta-openembedded*, as the *kexec-tools* recipe *RDEPENDS* on it.
  - The *tcl-8* recipe was added back to support the build of *expect*.
  - Add the *libdisplay-info* recipe, an EDID and DisplayID library, required for Weston 14.0.1 and newer.
  - The *hwdata* recipe was imported from *meta-openembedded*, a recipe for hardware identification and configuration data, needed by *libdisplay-info*.
  - The *cve-update-db-native* was restored from *kirkstone* and can be used to update the CVE National Vulnerability Database (NVD). Add support for the FKIE-CAD (<https://github.com/fkie-cad/nvd-json-data-feeds>) CVE source for it.
  - The *rpm-sequoia-crypto-policy* to ship a crypto policy file for the *rpm-sequoia* recipe.
  - The *libsass* and *sassc* for the C/C++ port of the Sass CSS pre-compiler, required by the *libadwaita* recipe.
  - *python3-roman-numerals-py*: module providing utilities for working with well-formed Roman numerals. *python3-sphinx* relies on this recipe.
  - The *fastfloat* recipe, a header-only library for fast number parsing. This will be a dependency for the *vte* recipe in later versions.
  - The *avahi-libnss-mdns* was renamed from *libnss-mdns*.
  - The *cargo-c* was renamed from *cargo-c-native*.
  - The *tcl8* recipe was added to support the failing build of *expect*. The *tcl* recipe (version 9) remains the main recipe for this component.
  - The *sdoc* recipe is imported from <https://layers.openembedded.org/layerindex/branch/master/layer/meta-wayland> to support the generation of the man-pages of *kdoc*.
- New core classes:
  - New *uki* class for building Unified Kernel Images (UKI). Associated OEQA tests were also added for this class.
  - New *cython* class for python recipes that require Cython for their compilation. Existing recipes depending on Cython now inherit this class. This class also strips potential build paths in the compilation output for reproducibility.



- New *ptest-python-pytest* class to automatically configure *ptest* for Python packages using the *pytest* unit test framework.
- Architecture-specific changes:
  - `tune-cortexa32`: set tune feature to `armv8a`.
  - Add the `loongarch64` architecture for the `grub2` and `llvm` recipes. It was also added to build with `musl` as the toolchain.
- QEMU / `runqemu` changes:
  - `qemu/machine`: change the `QEMU_EXTRAOPTIONS_${TUNE_PKGARCH}` syntax in QEMU machine definitions to `QEMU_EXTRAOPTIONS:tune-${TUNE_PKGARCH}` to follow the same patterns as other QEMU-related variables.
- Documentation changes:
  - Use `rsvg` as a replacement of `inkscape` to convert `svg` files in the documentation.
  - The `cve` role was replaced by `cve_nist` to avoid a conflict with more recent version of Sphinx.
  - New documentation on the multiconfig feature: *Building Images for Multiple Targets With Multiconfig*.
  - New documentation on `bblock`: *Locking and Unlocking Recipes Using bblock*.
- Go changes:
  - The *go-mod* class now sets an internal variable `GO_MOD_CACHE_DIR` to enable the use of the Go module fetchers for downloading and unpacking module dependencies to the module cache.
  - Make the *do\_compile* task run before *do\_populate\_lic* in the *go-mod* class so license files are found by *do\_populate\_lic* after the `go install` command is run in *do\_compile*.
- Rust changes:
  - `rust-target-config`: Update the data layout for the *x86-64* target, as it was different in Rust from LLVM, which produced a data layout error.
  - The *PACKAGECONFIG\_CONFARGS* value is now passed to the `cargo build` command, which means that Rust recipes can now properly define their *PACKAGECONFIG* configuration.
- Wic Image Creator changes:
  - Allow the `--exclude-path` option to exclude symlinks.
  - Add the variable *WIC\_SECTOR\_SIZE* to control the sector size of Wic images.
  - `bootimg-efi`: Support "+" symbol in filenames passed in *IMAGE\_EFI\_BOOT\_FILES*.
- SDK-related changes:
  - Add support for ZST-compression through *SDK\_ARCHIVE\_TYPE*, by setting its value to `tar.zst`.
  - The `debug-tweaks` features were removed from `-sdk` images (`core-image-*-sdk.bb`).
  - Enable `ipv6`, `acl`, and `xattr` in *DISTRO\_FEATURES\_NATIVESDK*.
  - Toolchain SDKs (`meta-toolchain`) now properly supports the `usrmerge` feature (part of *DISTRO\_FEATURES*).

- The `pipefail` shell option is now added to the SDK installer script.
- Testing-related changes:
  - `oeqa/postactions`: Fix archive retrieval from target.
  - `oeqa/selftest/gcc`: Fix kex exchange identification error.
  - `oeqa/utis/qemurunner`: support ignoring vt100 escape sequences.
  - `oeqa`: support passing custom boot patterns to `runqemu`.
  - `oeqa/selftest/cases`: add basic U-boot and Barebox tests.
  - `oeqa/selftest/rust`: skip on all MIPS platforms.
  - Lots of changes and improvements to the *Toaster* OEQA tests.
  - `oeqa/selftest`: add a test for bitbake "-e" and "-getvar" difference.
  - `oeqa/selftest`: Fix failure when configuration contains `BBLAYERS:append`
  - `oeqa/ssh`: improve performance and log sizes when handling large files.
  - `oeqa/poisoning`: fix and improve gcc include poisoning tests.
- Utility script changes:
  - The `patchreview.py` script now uses the `check_upstream_status` from `oe.qa` to get patch statuses.
  - `resulttool`:
    - \* Allow store to filter to specific revisions (`--revision` flag).
    - \* Use single space indentation in JSON output, to save disk space.
    - \* Add `--logfile-archive` option to store and archive log files separately.
    - \* Handle LTP raw logs as well as Ptest.
  - `yocto-check-layer`:
    - \* Check for the presence of a `SECURITY.md` file in layers and make it mandatory.
    - \* The *yocto-check-layer* class now uses `CHECKLAYER_REQUIRED_TESTS` to get the list of QA checks to verify when running the `yocto-check-layer` script.
  - New `oe-image-files-spdx` script utility directory under `scripts/contrib` to that processes the SPDX 3.0.1 output from a build and lists all the files on the root file system with their checksums.
  - `install-buildtools`:
    - \* Add the `--downloads-directory` argument to the script to allow specifying the location of the artifact download directory.
    - \* The download URL are now stored next to the download artifacts for traceability.
  - New `clean-hashserver-database` under `scripts/` that can be used to clean the hashserver database based on the files available in the `sstate` directory (see *Equivalenza degli Hash* for more information).

- BitBake changes:
  - Add a new concept of configuration fragment, which allows providing configuration snippets contained in layers in a structured and controlled way. For more information, see the [addfragments Directive](#) section of the BitBake User Manual.
  - Add a new `include_all` directive, which can be used to include multiple files present in the same location in different layers.
  - Fetcher related changes (`fetch2`):
    - \* Do not preserve ownership when unpacking.
    - \* switch from `Sqlite persist_data` to a standard cache file for checksums, and drop `persist_data`.
    - \* add support for GitHub codespaces by adding the `GITHUB_TOKEN` to the list of variables exported during `git` invocations.
    - \* set User-Agent to 'bitbake/version' instead of a "fake mozilla" user agent.
    - \* `wget`: handle HTTP 308 Permanent Redirect.
    - \* `wget`: increase timeout to 100s from 30s to match CDN worst response time.
    - \* Add support for fast initial shallow fetch. The fetcher will prefer an initial shallow clone, but will re-utilize an existing bare clone if there is one. If the remote server does not allow shallow fetches, the fetcher falls back to a bare clone. This improves the data transfer size on the initial fetch of a repository, eliminates the need to use an HTTPS tarball `SRC_URI` to reduce data transfer, and allows SSH-based authentication when using non-public repos, so additional HTTPS tokens may not be required.
  - `compress`: use `lz4` instead of `lz4c`, as `lz4c` as been considered deprecated since 2018.
  - `server/process`: decrease idle/main loop frequency, as it is idle and main loops have socket select calls to know when to execute.
  - `bitbake-worker`:
    - \* improve bytearray truncation performance when large amounts of data are being transferred from the cooker to the worker.
    - \* `cooker`: increase the default pipe size from 64KB to 512KB for better efficiency when transferring large amounts of data.
  - `bitbake-getvar`: catch `NoProvider` exception to improve error readability when a recipe is not found with `--recipe`.
  - `bb/build`: add a function `bb.build.listtasks()` to list the tasks in a datastore.
  - Remove custom exception backtrace formatting, and replace occurrences of `bb.exception.format_exception()` by `traceback.format_exception()`.
  - `runqueue`: various performance optimizations including:
    - \* Fix performance of multiconfigs with large overlap.
    - \* Optimise `setscene` loop processing by starting where it was left off in the previous execution.

- knotty now hints the user if *MACHINE* was not set in the *build/conf/local.conf* file.
- utils: add Go mod h1 checksum support, specific to Go modules. Use with *goh1*.
- The parser now catches empty variable name assignments such as:

```
+= "value"
```

The previous code would have assigned *value* to the variable named *+*.

- hashserv: Add the *gc-mark-stream* command for batch hash marking.

- Packaging changes:

- systemd: extract dependencies from *.note.dlopen* ELF segments, to better detect dynamically linked libraries at runtime.
- package\_rpm: use ZSTD's default compression level from the variable *ZSTD\_COMPRESSION\_LEVEL*.
- package\_rpm: restrict RPM packaging to 4 threads to improve the compression speed.
- sign\_rpm: rpm needs the sequoia *PACKAGECONFIG* config set to be able to generate signed packages.

- LLVM related changes:

- Set *LLVM\_HOST\_TRIPLE* for cross-compilation, which is recommended when cross-compiling Llv.

- SPDX-related changes:

- SPDX 3.0:
  - \* Find local sources when searching for debug sources.
  - \* Map *git* URIs to *git*.
  - \* Link license and build by alias instead of SPDX ID.
- Fix SPDX tasks not running when code changes (use of *file-checksums*).

- devtool changes:

- Remove the "*S* = *WORKDIR*" workaround as now *S* cannot be equal to *WORKDIR*.
- The already broken *--debug-build-config* option of *devtool ide-sdk* has been replaced by a new *--debug-build* option of *devtool modify*. The new *devtool ide-sdk* workflow is: *devtool modify my-recipe --debug-build* followed by *devtool ide-sdk my-recipe my-image*.
- *create-spdx*: support line numbers for *NO\_GENERIC\_LICENSE* license types.
- *spdx30*: Adds a "contains" relationship that relates the root file system package to the files contained in it. If a package provides a file with a matching hash and path, it will be linked, otherwise a new File element will be created.
- The output of *devtool upgrade-status* is now sorted by recipe name.

- Patchtest-related changes:

- Refactor pattern definitions in a *patterns* module.
- Refactor and improve the *mbox* module.

- Split out result messages.
- Add a check for user name tags in patches (for example "fix added by @username").
- *insane* class related changes:
  - Only parse ELF if they are files and not symlinks.
  - Check for `RUNPATH` in addition to `RPATH` in binaries.
  - Ensure *insane* tasks of dependencies run in builds when expected.
- Security changes:
  - The `PIE` gcc flag is now passed for the *powerpc* architecture after a bugfix in gcc ([https://gcc.gnu.org/bugzilla/show\\_bug.cgi?id=81170](https://gcc.gnu.org/bugzilla/show_bug.cgi?id=81170)).
  - `openssh`: be more restrictive on private key file permissions by setting them from the *do\_install* task.
- `cve-check` changes:
  - Update the *DL\_DIR* database location name (`${DL_DIR}/CVE_CHECK2`).
  - Add the field "modified" to the JSON report (from "NVD-modified").
  - Add support for CVSS v4.0.
  - Fix malformed cve status description with `:` characters.
  - Restore the `CVE_CHECK_SHOW_WARNINGS` variable and functionality. It currently prints warning message for every unpatched CVE the `cve-check` class finds.
  - Users can control the NVD database source using the `NVD_DB_VERSION` variable with possible values `NVD1`, `NVD2`, or `FKIE`.
  - The default feed for CVEs is now `FKIE` instead of `NVD2` (see `NVD_DB_VERSION` for more information).
- New *PACKAGECONFIG* options for individual recipes:
  - `perf`: `zstd`
  - `ppp`: `pam`, `openssl`
  - `libpciaccess`: `zlib`
  - `gdk-pixbuf`: `gif`, `others`
  - `libpam`: `selinux`
  - `libsecret`: `pam`
  - `rpm`: `sequoia`
  - `systemd`: `apparmor`, `fido`, `mountfsd`, `nsresourced`
  - `ovmf`: `debug`
  - `webkitgtk`: `assertions`
  - `iproute2`: `iptables`
  - `man-db`: `col`

- Systemd related changes:
  - systemd:
    - \* set better sane time at startup by creating the `clock-epoch` file in `${libdir}` if the `set-time-epoch` *PACKAGECONFIG* config is set.
    - \* really disable Predictable Network Interface names if the `pni-names` feature is not part of *DISTRO\_FEATURES*. Previously it was only really disabled for QEMU machines.
    - \* split `networkd` into its own package named `systemd-networkd`.
  - systemd-bootchart: now supports the 32-bit *riscv* architecture.
  - systemd-boot: now supports the *riscv* architecture.
  - systemd-serialgetty:
    - \* the recipe no longer sets a default value for *SERIAL\_CONSOLES*, and uses the one set in `bitbake.conf`.
    - \* the recipe no longer ships a copy of the `serial-getty@.service` as it is provided by systemd directly.
    - \* Don't set a default *SERIAL\_CONSOLES* value in the `systemd-serialgetty` recipe and take the global value that should already be set.
    - \* Replace custom unit files by existing unit files provided in the systemd source code.
  - User unit supports was improved. All the user units are now enabled by default.
  - The custom implementation of `systemctl` in *OpenEmbedded-Core (OE-Core)* was removed to use the upstream one. This `systemctl` binary is now compiled and used for systemd-related operations.
- *sanity* class changes:
  - Add a sanity check to validate that the C++ toolchain is functional on the host.
  - Add a sanity check to check that the C++ compiler on the host supports C++20.
  - Add a sanity check to verify that *TOPDIR* does not contain non-ASCII characters, as it may lead to unexpected build errors.
- Miscellaneous changes:
  - `bluez`: fix mesh build when building with musl.
  - `python3-pip`: the `pip` executable is now left and not deleted, and can be used instead of `pip3` and `pip2`.
  - `tar` image types are now more reproducible as the *IMAGE\_CMD* for `tar` now strips `atime` and `ctime` from the archive content.
  - *SOLIBSDEV* and *SOLIBS* are now defined for the *mingw32* architecture (`.dll`).
  - *rootfs-postcommands*: make `opkg` status reproducible.
  - The default *KERNEL\_CONSOLE* value is no longer `ttys0` but the first entry from the *SERIAL\_CONSOLES* variable.

- `virglrenderer`: add a patch to fix `-int-conversion` build issue.
- `ffmpeg`: disable asm optimizations for the `x86` architecture as PIC is required and `x86` ASM code is not PIC.
- `udev-extraconf`: fix the `network.sh` script that did not configure hotplugged interfaces.
- `classes-global/license`: move several functions and logic to library code in `meta/lib/oe/license.py`.
- The recipe `cairo` now disables the features `symbol-lookup`, `spectre`, and `tests` by default.
- The recipe `glib-2.0` now disables the feature `sysprof` by default.
- The recipe `gstreamer1.0-libav` now disables the feature `doc` by default.
- `rxvt-unicode`: change `virtual/x-terminal-emulator` from *PROVIDES* to *RPROVIDES* as `virtual-x-terminal-emulator`. Also make this recipe depend on the `x11` distro features with *REQUIRED\_DISTRO\_FEATURES*.
- `rxvt-unicode.inc`: disable the `terminfo` installation by setting `TIC` to `:` in *EXTRA\_OECONF*, to avoid host contamination.
- `matchbox-terminal`: add `x-terminal-emulator` as *RPROVIDES* and set *ALTERNATIVE* for the recipe.
- `default-providers.conf`: set `rxvt-unicode` as the default `virtual-x-terminal-emulator` runtime provider with *PREFERRED\_RPROVIDER*.
- `cve-update-nvd2-native`: updating the database will now result in an error if *BB\_NO\_NETWORK* is enabled and `CVE_DB_UPDATE_INTERVAL` is not set to `-1`. Users can control the NVD database source using the `NVD_DB_VERSION` variable with possible values `NVD1`, `NVD2`, or `FKIE`.
- `systemtap`: add `--with-extra-version="oe"` configure option to improve the reproducibility of the recipe.
- `python3`: package `tkinter`'s shared objects separately in the `python3-tkinter` package.
- `init-manager`: set the variable `VIRTUAL-RUNTIME_dev_manager` to `udev` by default in `meta/conf/distro/include/init-manager-none.inc` and `meta/conf/distro/include/init-manager-sysvinit.inc`, instead of `meta/recipes-core/packagegroups/packagegroup-core-boot.bb` only.  
  
Likewise, the same is done for `VIRTUAL-RUNTIME_keymaps` with `keymaps` as its default value.
- `seatd`: Create a `seat` group and package the `systemd` service `seatd.service` with correct permissions.  
  
That way, the `weston` user in `weston-init.bb` was added to the `seat` group to be able to properly establish connection between the Weston and the `seatd` socket.
- `webkitgtk`:
  - \* Fix build on 32bit arches with 64bit `time_t` only.
  - \* Disable JIT on RISCv64.
- *report-error*: Add *PN* to error report files.
- `initrdscripts`: add UBI support for mounting a live `ubifs` rootfs.

- `uboot-extlinux-config.bbclass`: add support for device tree overlays.
- `glibc`: add `ld.so.conf` to *CONFFILES*.
- `udev-extraconf`: Allow FAT mount group to be specified with *MOUNT\_GROUP*.
- New `bbverbnote` log utility which can be used to print on the console (equivalent to the `bb.verbnote` Python implementation).
- *grub-efi*: Add *GRUB\_TITLE* variable to set custom GRUB titles.
- `gawk`: Enable high precision arithmetic support by default (`mpfr` enabled by default in *PACKAGECONFIG*).
- `licenses`: Map the license `SGIv1` to `SGI-OpenGL`, as `SGIv1` is not an SPDX license identifier.
- Configuration files for the `b4` command-line tool was added to the different Yocto Project and OpenEmbedded repositories.
- `kernel-fitimage`: handle *multiconfig* dependency when *INITRAMFS\_MULTICONFIG* is set.
- `psplash`: when using the `systemd` feature from *DISTRO\_FEATURES*, start the `psplash` service when the `/dev/fb0` framebuffer is detected with Udev.
- `gdb`: is now compiled with xz support by default (`--with-lzma`).
- `busybox`: drop `net-tools` from the default `defconfig`, since these tools (`ifconfig`, etc.) have been deprecated since 2009.
- `perf` is built with `zstd` in *PACKAGECONFIG* by default.
- `boost`: add `charconv` to built libraries by default.
- `mirrors`: rationalise Debian mirrors to point at the canonical server (`deb.debian.org`) instead of country specific ones. This server is backed by a *CDN* to properly balance the server load.
- `lib: sbom30`: Add action statement for affected VEX statements with "Mitigation action unknown", as these are not tracked by the existing code.

## Known Issues in 5.2

- The `cve-check` class is based on the *National Vulnerability Database* (NVD). Since the beginning of 2024, the maintainers of this database have stopped annotating CVEs with the affected CPEs. This prevents the `cve-check` class to properly report CVEs as CPEs are used to match Yocto recipes with CVEs affecting them. As a result, the current CVE reports may look good but the reality is that some vulnerabilities are just not reported.

During that time, users may look up the 'CVE database <<https://www.cve.org/>>'\_\_ for entries concerning software they use, or follow release notes of such projects closely.

Please note, that the `cve-check` tool has always been a helper tool, and users are advised to always review the final result. Results of an automatic scan may not take into account configuration options, compiler options and other factors.



## Recipe License changes in 5.2

The following changes have been made to the *LICENSE* values set by recipes:

| Recipe                | Previous value                                                                                                            | New value                                                                                                                    |
|-----------------------|---------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------|
| babeltrace2           | MIT & GPL-2.0-only & LGPL-2.1-only & BSD-2-Clause                                                                         | MIT & GPL-2.0-only & LGPL-2.1-only & BSD-2-Clause & BSD-4-Clause & GPL-3.0-or-later & CC-BY-SA-4.0 & PSF-2.0                 |
| busybox               | GPL-2.0-only & bzip2-1.0.4                                                                                                | GPL-2.0-only & bzip2-1.0.6                                                                                                   |
| dbus-glib             | AFL-2.1   GPL-2.0-or-later                                                                                                | (AFL-2.1 & LGPL-2.0-or-later & MIT)   (GPL-2.0-or-later & LGPL-2.0-or-later & MIT)                                           |
| diffstat              | MIT                                                                                                                       | X11                                                                                                                          |
| doc-book-xsl-styleset | XSL                                                                                                                       | DocBook-XML                                                                                                                  |
| font-util             | Unicode-TOU & BSD-4-Clause & BSD-2-Clause                                                                                 | Unicode-TOU & MIT & X11 & BSD-2-Clause                                                                                       |
| json-glib             | LGPL-2.1-only                                                                                                             | LGPL-2.1-or-later                                                                                                            |
| libbsd                | BSD-3-Clause & BSD-4-Clause & ISC & PD                                                                                    | BSD-3-Clause & ISC & PD                                                                                                      |
| libxfont2             | MIT & MIT & BSD-4-Clause & BSD-2-Clause                                                                                   | MIT & MIT & BSD-4-Clause-UC & BSD-2-Clause                                                                                   |
| libxkbcommon          | MIT & MIT                                                                                                                 | MIT & MIT-open-group & HPND & HPND-sell-variant & X11                                                                        |
| man-pages             | GPL-2.0-or-later & GPL-2.0-only & GPL-1.0-or-later & BSD-2-Clause & BSD-3-Clause & BSD-4-Clause & MIT                     | GPL-2.0-or-later & GPL-2.0-only & GPL-1.0-or-later & BSD-2-Clause & BSD-3-Clause & BSD-4-Clause-UC & MIT                     |
| ppp                   | BSD-3-Clause & BSD-3-Clause-Attribution & GPL-2.0-or-later & LGPL-2.0-or-later & PD & RSA-MD & MIT                        | BSD-2-Clause & GPL-2.0-or-later & LGPL-2.0-or-later & PD & RSA-MD & MIT                                                      |
| tcf-agent             | EPL-1.0   EDL-1.0                                                                                                         | EPL-1.0   BSD-3-Clause                                                                                                       |
| unfs3                 | unfs3                                                                                                                     | BSD-3-Clause                                                                                                                 |
| usbutils              | GPL-2.0-or-later & (GPL-2.0-only   GPL-3.0-only)                                                                          | GPL-2.0-or-later & (GPL-2.0-only   GPL-3.0-only) & CC0-1.0 & LGPL-2.1-or-later & MIT                                         |
| util-linux            | GPL-1.0-or-later & GPL-2.0-only & GPL-2.0-or-later & LGPL-2.1-or-later & BSD-2-Clause & BSD-3-Clause & BSD-4-Clause & MIT | GPL-1.0-or-later & GPL-2.0-only & GPL-2.0-or-later & LGPL-2.1-or-later & BSD-2-Clause & BSD-3-Clause & BSD-4-Clause-UC & MIT |

## Security Fixes in 5.2

The following CVEs have been fixed:

| Recipe                      | CVE IDs                                                                                                                                                                                                                                                                                                                                                        |
|-----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| barebox                     | CVE-2025-26721, CVE-2025-26722, CVE-2025-26723, CVE-2025-26724, CVE-2025-26725                                                                                                                                                                                                                                                                                 |
| binutils                    | CVE-2024-53589, CVE-2025-1153                                                                                                                                                                                                                                                                                                                                  |
| curl                        | CVE-2024-8096, CVE-2024-9681, CVE-2024-11053, CVE-2025-0167, CVE-2025-0665, CVE-2025-0725                                                                                                                                                                                                                                                                      |
| expat                       | CVE-2024-8176, CVE-2024-50602                                                                                                                                                                                                                                                                                                                                  |
| ghostscript                 | CVE-2024-46951, CVE-2024-46952, CVE-2024-46953, CVE-2024-46954, CVE-2024-46955, CVE-2024-46956                                                                                                                                                                                                                                                                 |
| gnutls                      | CVE-2024-12243                                                                                                                                                                                                                                                                                                                                                 |
| go                          | CVE-2024-34155, CVE-2024-34156, CVE-2024-34158, CVE-2024-45336, CVE-2024-45341, CVE-2025-22866, CVE-2025-22870                                                                                                                                                                                                                                                 |
| grub                        | CVE-2024-45774, CVE-2024-45775, CVE-2024-45776, CVE-2024-45777, CVE-2024-45778, CVE-2024-45779, CVE-2024-45780, CVE-2024-45781, CVE-2024-45782, CVE-2024-45783, CVE-2024-56737, CVE-2025-0622, CVE-2025-0624, CVE-2025-0677, CVE-2025-0678, CVE-2025-0684, CVE-2025-0685, CVE-2025-0686, CVE-2025-0689, CVE-2025-0690, CVE-2025-1118, CVE-2025-1125            |
| gststreamer1.0              | CVE-2024-47606                                                                                                                                                                                                                                                                                                                                                 |
| gststreamer1.0-plugins-base | CVE-2024-47538, CVE-2024-47541, CVE-2024-47542, CVE-2024-47600, CVE-2024-47607, CVE-2024-47615, CVE-2024-47835                                                                                                                                                                                                                                                 |
| gststreamer1.0-plugins-good | CVE-2024-47537, CVE-2024-47539, CVE-2024-47540, CVE-2024-47543, CVE-2024-47544, CVE-2024-47545, CVE-2024-47546, CVE-2024-47596, CVE-2024-47597, CVE-2024-47598, CVE-2024-47599, CVE-2024-47601, CVE-2024-47602, CVE-2024-47603, CVE-2024-47606, CVE-2024-47613, CVE-2024-47774, CVE-2024-47775, CVE-2024-47776, CVE-2024-47777, CVE-2024-47778, CVE-2024-47834 |
| libarchive                  | CVE-2024-57970, CVE-2025-1632, CVE-2025-25724                                                                                                                                                                                                                                                                                                                  |
| libcap                      | CVE-2025-1390                                                                                                                                                                                                                                                                                                                                                  |
| libsndfile1                 | CVE-2024-50612                                                                                                                                                                                                                                                                                                                                                 |
| libtasn1                    | CVE-2024-12133                                                                                                                                                                                                                                                                                                                                                 |
| libxml2                     | CVE-2024-56171, CVE-2025-24928                                                                                                                                                                                                                                                                                                                                 |
| ofono                       | CVE-2024-7539, CVE-2024-7540, CVE-2024-7541, CVE-2024-7542                                                                                                                                                                                                                                                                                                     |
| omvf                        | CVE-2023-45236, CVE-2023-45237, CVE-2024-25742                                                                                                                                                                                                                                                                                                                 |
| openssh                     | CVE-2025-26465, CVE-2025-26466                                                                                                                                                                                                                                                                                                                                 |
| openssl                     | CVE-2024-9143, CVE-2024-12797, CVE-2024-13176                                                                                                                                                                                                                                                                                                                  |
| orc                         | CVE-2024-40897                                                                                                                                                                                                                                                                                                                                                 |
| python3                     | CVE-2025-0938, CVE-2024-12254                                                                                                                                                                                                                                                                                                                                  |
| qemu                        | CVE-2024-6505                                                                                                                                                                                                                                                                                                                                                  |

continues on next page

Tabella 6 – continua dalla pagina precedente

| Recipe         | CVE IDs                                                                                                                                       |
|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------|
| rsync          | CVE-2024-12084, CVE-2024-12085, CVE-2024-12086, CVE-2024-12087, CVE-2024-12088, CVE-2024-12747                                                |
| ruby           | CVE-2024-41123, CVE-2024-41946                                                                                                                |
| rust           | CVE-2024-43402                                                                                                                                |
| socat          | CVE-2024-54661                                                                                                                                |
| tiff           | CVE-2023-6277, CVE-2023-6228, CVE-2023-52356                                                                                                  |
| vim            | CVE-2024-45306, CVE-2024-47814, CVE-2025-1215, CVE-2025-22134, CVE-2025-24014, CVE-2025-26603, CVE-2025-27423, CVE-2025-29768                 |
| webkitgtk      | CVE-2025-24143, CVE-2025-24150, CVE-2025-24158, CVE-2025-24162                                                                                |
| wpa-supPLICant | CVE-2024-5290                                                                                                                                 |
| xserver-xorg   | CVE-2024-9632, CVE-2025-26594, CVE-2025-26595, CVE-2025-26596, CVE-2025-26597, CVE-2025-26598, CVE-2025-26599, CVE-2025-26600, CVE-2025-26601 |
| xwayland       | CVE-2024-9632, CVE-2025-26594, CVE-2025-26595, CVE-2025-26596, CVE-2025-26597, CVE-2025-26598, CVE-2025-26599, CVE-2025-26600, CVE-2025-26601 |

## Recipe Upgrades in 5.2

| Recipe               | Previous version | New version |
|----------------------|------------------|-------------|
| adwaita-icon-theme   | 46.2             | 48.0        |
| alsa-lib             | 1.2.12           | 1.2.13      |
| alsa-ucm-conf        | 1.2.12           | 1.2.13      |
| alsa-utils           | 1.2.12           | 1.2.13      |
| appstream            | 1.0.3            | 1.0.4       |
| at-spi2-core         | 2.52.0           | 2.56.0      |
| autoconf-archive     | 2023.02.20       | 2024.10.16  |
| babeltrace2          | 2.0.6            | 2.1.0       |
| base-passwd          | 3.6.4            | 3.6.6       |
| bash                 | 5.2.32           | 5.2.37      |
| bash-completion      | 2.14.0           | 2.16.0      |
| bc                   | 1.07.1           | 1.08.1      |
| bind                 | 9.20.1           | 9.20.6      |
| binutils             | 2.43.1           | 2.44        |
| binutils-cross       | 2.43.1           | 2.44        |
| binutils-cross-canac | 2.43.1           | 2.44        |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe           | Previous version         | New version              |
|------------------|--------------------------|--------------------------|
| binu-            | 2.43.1                   | 2.44                     |
| tils-crosssdk    |                          |                          |
| binu-            | 2.43.1                   | 2.44                     |
| tils-testsuite   |                          |                          |
| bluez5           | 5.78                     | 5.79                     |
| boost            | 1.86.0                   | 1.87.0                   |
| boo-             | 1.86.0                   | 1.87.0                   |
| st-build-native  |                          |                          |
| btrfs-tools      | 6.10.1                   | 6.13                     |
| build-appliance- | 15.0.0 (6a5ba188b79e...) | 15.0.0 (2fe7f46e1779...) |
| busybox          | 1.36.1                   | 1.37.0                   |
| busy-            | 1.36.1                   | 1.37.0                   |
| box-inittab      |                          |                          |
| ca-certificates  | 20240203                 | 20241223                 |
| cairo            | 1.18.2                   | 1.18.4                   |
| cargo            | 1.79.0                   | 1.84.1                   |
| ccache           | 4.10.2                   | 4.11                     |
| chrpath          | 0.16                     | 0.18                     |
| cmake            | 3.30.2                   | 3.31.6                   |
| cmake-native     | 3.30.2                   | 3.31.6                   |
| connman          | 1.42                     | 1.43                     |
| coreutils        | 9.5                      | 9.6                      |
| cracklib         | 2.10.2                   | 2.10.3                   |
| createrepo-c     | 1.1.4                    | 1.2.0                    |
| cross-localedef- | 2.40+git                 | 2.41+git                 |
| cups             | 2.4.10                   | 2.4.11                   |
| curl             | 8.9.1                    | 8.12.1                   |
| dbus             | 1.14.10                  | 1.16.2                   |
| dbus-glib        | 0.112                    | 0.114                    |
| debianutils      | 5.20                     | 5.21                     |
| debugedit        | 5.0                      | 5.1                      |
| desk-            | 0.27                     | 0.28                     |
| top-file-utils   |                          |                          |
| dhcpcd           | 10.0.10                  | 10.2.2                   |
| diffoscope       | 277                      | 289                      |
| diffstat         | 1.66                     | 1.67                     |
| diffutils        | 3.10                     | 3.11                     |
| dnf              | 4.21.1                   | 4.22.0                   |
| dropbear         | 2024.85                  | 2024.86                  |
| dtc              | 1.7.0                    | 1.7.2                    |
| ed               | 1.20.2                   | 1.21                     |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe                   | Previous version      | New version           |
|--------------------------|-----------------------|-----------------------|
| efivar                   | 39+39+git             | 39                    |
| elfutils                 | 0.191                 | 0.192                 |
| ell                      | 0.68                  | 0.74                  |
| epiphany                 | 46.3                  | 48.0                  |
| erofs-utils              | 1.8.1                 | 1.8.5                 |
| ethtool                  | 6.10                  | 6.11                  |
| expat                    | 2.6.4                 | 2.7.0                 |
| ffmpeg                   | 7.0.2                 | 7.1.1                 |
| file                     | 5.45                  | 5.46                  |
| fmt                      | 11.0.2                | 11.1.4                |
| fribidi                  | 1.0.15                | 1.0.16                |
| gawk                     | 5.3.0                 | 5.3.1                 |
| gcr                      | 4.3.0                 | 4.3.1                 |
| gdb                      | 15.1                  | 16.2                  |
| gdb-cross                | 15.1                  | 16.2                  |
| gdb-cross-canadi         | 15.1                  | 16.2                  |
| gettext                  | 0.22.5                | 0.23.1                |
| get-<br>text-minimal-nat | 0.22.5                | 0.23.1                |
| ghostscript              | 10.04.0               | 10.05.0               |
| gi-docgen                | 2024.1                | 2025.3                |
| git                      | 2.46.1                | 2.49.0                |
| glib-2                   | .0 2.80.4             | 2.84.0                |
| glib-2                   | .0-initial 2.80.4     | 2.84.0                |
| glibc                    | 2.40+git              | 2.41+git              |
| glibc-locale             | 2.40+git              | 2.41+git              |
| glibc-mtrace             | 2.40+git              | 2.41+git              |
| glibc-scripts            | 2.40+git              | 2.41+git              |
| glibc-testsuite          | 2.40+git              | 2.41+git              |
| glibc-y2038-test         | 2.40+git              | 2.41+git              |
| glslang                  | 1.3.290.0             | 1.4.309.0             |
| gnu-efi                  | 3.0.18                | 4.0.0                 |
| gnupg                    | 2.5.0                 | 2.5.5                 |
| gnutls                   | 3.8.6                 | 3.8.9                 |
| go                       | 1.22.12               | 1.24.1                |
| go-binary-native         | 1.22.12               | 1.24.1                |
| go-cross-canadi          | 1.22.12               | 1.24.1                |
| go-cross-core2-3         | 1.22.12               | 1.24.1                |
| go-crosssdk              | 1.22.12               | 1.24.1                |
| go-helloworld            | 0.1 (39e772fc2670...) | 0.1 (d7b0ac127859...) |
| go-runtime               | 1.22.12               | 1.24.1                |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe           | Previous version          | New version               |
|------------------|---------------------------|---------------------------|
| gob-             | 1.80.1                    | 1.84.0                    |
| ject-introspecti |                           |                           |
| gpgme            | 1.23.2                    | 1.24.2                    |
| gset-            | 46.1                      | 48.0                      |
| tings-desktop-sc |                           |                           |
| gst-devtools     | 1.24.10                   | 1.24.12                   |
| gststreamer1.0   | 1.24.10                   | 1.24.12                   |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-libav          |                           |                           |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-plugins-bad    |                           |                           |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-plugins-base   |                           |                           |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-plugins-good   |                           |                           |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-plugins-ugly   |                           |                           |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-python         |                           |                           |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-rtsp-server    |                           |                           |
| gststreamer1.    | 1.24.10                   | 1.24.12                   |
| 0-vaapi          |                           |                           |
| gtk4             | 4.14.5                    | 4.18.1                    |
| harfbuzz         | 9.0.0                     | 10.4.0                    |
| hwlatdetect      | 2.7                       | 2.8                       |
| i2c-tools        | 4.3                       | 4.4                       |
| icu              | 75-1                      | 76-1                      |
| ifupdown         | 0.8.43                    | 0.8.44                    |
| igt-gpu-tools    | 1.28                      | 1.30                      |
| inetutils        | 2.5                       | 2.6                       |
| init-system-help | 1.66                      | 1.68                      |
| iproute2         | 6.10.0                    | 6.13.0                    |
| iptables         | 1.8.10                    | 1.8.11                    |
| iputils          | 20240117                  | 20240905                  |
| iso-codes        | 4.16.0                    | 4.17.0                    |
| json-c           | 0.17                      | 0.18                      |
| json-glib        | 1.8.0                     | 1.10.6                    |
| kbd              | 2.6.4                     | 2.7.1                     |
| kern-tools-nativ | 0.3+git (7160ebe8b865...) | 0.3+git (bfca22a52ec5...) |
| kexec-tools      | 2.0.29                    | 2.0.30                    |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe                | Previous version            | New version                 |
|-----------------------|-----------------------------|-----------------------------|
| kmod                  | 33                          | 34.1                        |
| kmscube               | 0.0.1+git (b2f97f53e01e...) | 0.0.1+git (311eaaaa473d...) |
| less                  | 661                         | 668                         |
| libadwaita            | 1.5.3                       | 1.7.0                       |
| libarchive            | 3.7.4                       | 3.7.8                       |
| libassuan             | 3.0.1                       | 3.0.2                       |
| libcap                | 2.70                        | 2.75                        |
| libdnf                | 0.73.3                      | 0.73.4                      |
| libdrm                | 2.4.123                     | 2.4.124                     |
| libedit               | 20240808-3.1                | 20250104-3.1                |
| libexif               | 0.6.24                      | 0.6.25                      |
| libffi                | 3.4.6                       | 3.4.7                       |
| libgit2               | 1.8.1                       | 1.9.0                       |
| libgpg-error          | 1.50                        | 1.51                        |
| libical               | 3.0.18                      | 3.0.20                      |
| libice                | 1.1.1                       | 1.1.2                       |
| libidn2               | 2.3.7                       | 2.3.8                       |
| libinput              | 1.26.1                      | 1.27.1                      |
| libjitteren-<br>tropy | 3.5.0                       | 3.6.2                       |
| libmatchbox           | 1.12                        | 1.13                        |
| libnl                 | 3.10.0                      | 3.11.0                      |
| libnotify             | 0.8.3                       | 0.8.4                       |
| libpam                | 1.6.1                       | 1.7.0                       |
| libpcre2              | 10.44                       | 10.45                       |
| libpipeline           | 1.5.7                       | 1.5.8                       |
| libpng                | 1.6.43                      | 1.6.47                      |
| libportal             | 0.7.1                       | 0.9.1                       |
| libproxy              | 0.5.8                       | 0.5.9                       |
| librepo               | 1.18.1                      | 1.19.0                      |
| librsvg               | 2.58.2                      | 2.59.2                      |
| libsdl2               | 2.30.7                      | 2.32.2                      |
| libseccomp            | 2.5.5                       | 2.6.0                       |
| libsecret             | 0.21.4                      | 0.21.6                      |
| libslirp              | 4.8.0                       | 4.9.0                       |
| libsm                 | 1.2.4                       | 1.2.6                       |
| libsolv               | 0.7.30                      | 0.7.31                      |
| libsoup               | 3.6.0                       | 3.6.4                       |
| libssh2               | 1.11.0                      | 1.11.1                      |
| libstd-rs             | 1.79.0                      | 1.84.1                      |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe                     | Previous version        | New version |
|----------------------------|-------------------------|-------------|
| libte-<br>st-warnings-perl | 0.033                   | 0.038       |
| libtirpc                   | 1.3.5                   | 1.3.6       |
| libtool                    | 2.5.2                   | 2.5.4       |
| libtool-cross              | 2.5.2                   | 2.5.4       |
| libtool-native             | 2.5.2                   | 2.5.4       |
| libtraceevent              | 1.8.3                   | 1.8.4       |
| lib-<br>try-tiny-perl      | 0.31                    | 0.32        |
| libubootenv                | 0.3.5                   | 0.3.6       |
| libunistring               | 1.2                     | 1.3         |
| liburcu                    | 0.14.1                  | 0.15.1      |
| libuv                      | 1.48.0                  | 1.50.0      |
| libwebp                    | 1.4.0                   | 1.5.0       |
| libwpe                     | 1.16.0                  | 1.16.2      |
| libx11                     | 1.8.10                  | 1.8.12      |
| libxau                     | 1.0.11                  | 1.0.12      |
| libxcrypt                  | 4.4.36                  | 4.4.38      |
| libx-<br>crypt-compat      | 4.4.36                  | 4.4.38      |
| libxcursor                 | 1.2.2                   | 1.2.3       |
| libxcvt                    | 0.1.2                   | 0.1.3       |
| libxi                      | 1.8.1                   | 1.8.2       |
| libxkbcommon               | 1.7.0                   | 1.8.1       |
| libxmlb                    | 0.3.19                  | 0.3.22      |
| libxrender                 | 0.9.11                  | 0.9.12      |
| libxshmfence               | 1.3.2                   | 1.3.3       |
| libxslt                    | 1.1.42                  | 1.1.43      |
| libxt                      | 1.3.0                   | 1.3.1       |
| libxv                      | 1.0.12                  | 1.0.13      |
| libxxf86vm                 | 1.1.5                   | 1.1.6       |
| lighttpd                   | 1.4.76                  | 1.4.77      |
| linux-firmware             | 20240909                | 20250311    |
| li-<br>nux-libc-headers    | 6.10                    | 6.12        |
| linux-yocto                | 6.6.75+git, 6.10.14+git | 6.12.19+git |
| li-<br>nux-yocto-dev       | 6.11+git                | 6.14+git    |
| linux-yocto-rt             | 6.6.75+git, 6.10.14+git | 6.12.19+git |
| li-<br>nux-yocto-tiny      | 6.6.75+git, 6.10.14+git | 6.12.19+git |

continues on next page



Tabella 7 – continua dalla pagina precedente

| Recipe                 | Previous version            | New version                 |
|------------------------|-----------------------------|-----------------------------|
| llvm                   | 18.1.8                      | 20.1.0                      |
| log4cplus              | 2.1.1                       | 2.1.2                       |
| lsof                   | 4.99.3                      | 4.99.4                      |
| ltp                    | 20240524                    | 20250130                    |
| lttng-modules          | 2.13.14                     | 2.13.17                     |
| lzip                   | 1.24.1                      | 1.25                        |
| lzlib                  | 1.14                        | 1.15                        |
| man-db                 | 2.12.1                      | 2.13.0                      |
| man-pages              | 6.9.1                       | 6.13                        |
| mc                     | 4.8.32                      | 4.8.33                      |
| mesa-demos             | 8.5.0                       | 9.0.0                       |
| meson                  | 1.5.1                       | 1.7.0                       |
| minicom                | 2.9                         | 2.10                        |
| mmc-utils              | 0.1+git (123fd8b2ac39...)   | 0.1+git (2aef4cd9a84d...)   |
| mpg123                 | 1.32.7                      | 1.32.10                     |
| msmtp                  | 1.8.26                      | 1.8.28                      |
| mtd-utils              | 2.2.0                       | 2.3.0                       |
| mttools                | 4.0.44                      | 4.0.48                      |
| musl                   | 1.2.5+git (dd1e63c3638d...) | 1.2.5+git (c47ad25ea3b4...) |
| native-<br>sdk-libtool | 2.5.2                       | 2.5.4                       |
| netbase                | 6.4                         | 6.5                         |
| nettle                 | 3.10                        | 3.10.1                      |
| nfs-utils              | 2.6.4                       | 2.8.2                       |
| nghttp2                | 1.63.0                      | 1.65.0                      |
| npth                   | 1.7                         | 1.8                         |
| numactl                | 2.0.18                      | 2.0.19                      |
| ofono                  | 2.10                        | 2.15                        |
| opensbi                | 1.5.1                       | 1.6                         |
| openssh                | 9.8p1                       | 9.9p2                       |
| openssl                | 3.3.1                       | 3.4.1                       |
| orc                    | 0.4.40                      | 0.4.41                      |
| ovmf                   | edk2-stable202402           | edk2-stable202411           |
| pango                  | 1.54.0                      | 1.56.2                      |
| piglit                 | 1.0+gitr (c11c9374c144...)  | 1.0+gitr (fc8179d31904...)  |
| pixman                 | 0.42.2                      | 0.44.2                      |
| pkgconf                | 2.3.0                       | 2.4.3                       |
| ppp                    | 2.5.0                       | 2.5.2                       |
| procps                 | 4.0.4                       | 4.0.5                       |
| psplash                | 0.1+git (ecc191375669...)   | 0.1+git (1f64c654129f...)   |
| ptest-runner           | 2.4.5+git                   | 2.4.5.1                     |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe               | Previous version          | New version               |
|----------------------|---------------------------|---------------------------|
| puzzles              | 0.0+git (1c1899ee1c4e...) | 0.0+git (7da464122232...) |
| python3              | 3.12.9                    | 3.13.2                    |
| python3-attrs        | 24.2.0                    | 25.3.0                    |
| python3-babel        | 2.16.0                    | 2.17.0                    |
| python3-bcrypt       | 4.2.0                     | 4.3.0                     |
| py-thon3-beartype    | 0.18.5                    | 0.20.0                    |
| python3-build        | 1.2.1                     | 1.2.2                     |
| py-thon3-certifi     | 2024.8.30                 | 2025.1.31                 |
| python3-cffi         | 1.17.0                    | 1.17.1                    |
| python3-click        | 8.1.7                     | 8.1.8                     |
| py-thon3-cryptograf  | 42.0.8                    | 44.0.2                    |
| py-thon3-cryptograf  | 42.0.8                    | 44.0.2                    |
| python3-cython       | 3.0.11                    | 3.0.12                    |
| python3-dbus         | 1.3.2                     | 1.4.0                     |
| py-thon3-dbusmock    | 0.32.1                    | 0.33.0                    |
| python3-dtc          | 1.7.0                     | 1.7.2                     |
| py-thon3-dtschema    | 2024.5                    | 2025.2                    |
| py-thon3-flit-core   | 3.9.0                     | 3.11.0                    |
| python3-gitdb        | 4.0.11                    | 4.0.12                    |
| py-thon3-hatchling   | 1.25.0                    | 1.27.0                    |
| py-thon3-hypothesis  | 6.111.2                   | 6.129.2                   |
| python3-idna         | 3.8                       | 3.10                      |
| python3-jinja2       | 3.1.4                     | 3.1.6                     |
| py-thon3-jjsonschema | 2023.12.1                 | 2024.10.1                 |
| py-thon3-license-ex  | 30.3.1                    | 30.4.1                    |
| python3-lxml         | 5.3.0                     | 5.3.1                     |
| python3-mako         | 1.3.5                     | 1.3.9                     |
| py-thon3-markdown    | 3.6                       | 3.7                       |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe                  | Previous version | New version |
|-------------------------|------------------|-------------|
| py-thon3-markupsafe     | 2.1.5            | 3.0.2       |
| py-thon3-maturin        | 1.7.1            | 1.8.3       |
| py-thon3-meson-python   | 0.16.0           | 0.17.1      |
| py-thon3-more-itertools | 10.4.0           | 10.6.0      |
| python3-numpy           | 1.26.4           | 2.2.3       |
| py-thon3-packaging      | 24.1             | 24.2        |
| python3-pip             | 24.2             | 25.0.1      |
| py-thon3-poetry-core    | 1.9.0            | 2.1.1       |
| python3-psutil          | 6.0.0            | 7.0.0       |
| python3-pyasn1          | 0.6.0            | 0.6.1       |
| py-thon3-pycairo        | 1.26.1           | 1.27.0      |
| py-thon3-pycryptodome   | 3.20.0           | 3.22.0      |
| py-thon3-pycryptodome   | 3.20.0           | 3.22.0      |
| py-thon3-pyelftools     | 0.31             | 0.32        |
| py-thon3-pygments       | 2.18.0           | 2.19.1      |
| py-thon3-pyobject       | 3.48.2           | 3.52.2      |
| py-thon3-pyopenssl      | 24.2.1           | 25.0.0      |
| py-thon3-pyparsing      | 3.1.4            | 3.2.1       |
| py-thon3-pyproject      | 1.0.0            | 1.2.0       |
| py-thon3-pyproject      | 0.8.0            | 0.9.1       |
| python3-pytest          | 8.3.2            | 8.3.5       |
| py-thon3-pytest-sugar   | 0.13.1           | 0.14.1      |
| python3-pytz            | 2024.1           | 2025.1      |
| python3-rdflib          | 7.0.0            | 7.1.3       |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe              | Previous version | New version  |
|---------------------|------------------|--------------|
| py-thon3-referencir | 0.35.1           | 0.36.2       |
| py-thon3-rpds-py    | 0.20.0           | 0.22.3       |
| py-thon3-ruamel-yam | 0.18.6           | 0.18.10      |
| python3-scons       | 4.8.0            | 4.9.0        |
| py-thon3-setuptools | 72.1.0           | 76.0.0       |
| py-thon3-setuptools | 1.10.1           | 1.11.0       |
| py-thon3-setuptools | 8.1.0            | 8.2.0        |
| python3-six         | 1.16.0           | 1.17.0       |
| py-thon3-spdx-tools | 0.8.2            | 0.8.3        |
| python3-sphinx      | 8.0.2            | 8.2.1        |
| py-thon3-sphinx-rtc | 2.0.0            | 3.0.2        |
| py-thon3-trove-clas | 2024.7.2         | 2025.3.13.13 |
| py-thon3-typogrify  | 2.0.7            | 2.1.0        |
| py-thon3-urllib3    | 2.2.2            | 2.3.0        |
| py-thon3-websockets | 13.0.1           | 15.0.1       |
| python3-wheel       | 0.44.0           | 0.45.1       |
| py-thon3-xmltodict  | 0.13.0           | 0.14.2       |
| py-thon3-yamllint   | 1.35.1           | 1.36.0       |
| python3-zipp        | 3.20.1           | 3.21.0       |
| qemu                | 9.0.2            | 9.2.0        |
| qemu-native         | 9.0.2            | 9.2.0        |
| qe-mu-system-native | 9.0.2            | 9.2.0        |
| re2c                | 3.1              | 4.1          |
| repo                | 2.46             | 2.52         |
| rpm                 | 4.19.1.1         | 4.20.0       |
| rsync               | 3.3.0            | 3.4.1        |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe                     | Previous version | New version |
|----------------------------|------------------|-------------|
| rt-tests                   | 2.7              | 2.8         |
| ruby                       | 3.3.4            | 3.4.2       |
| rust                       | 1.79.0           | 1.84.1      |
| ru-<br>st-cross-canadian   | 1.79.0           | 1.84.1      |
| rust-llvm                  | 1.79.0           | 1.84.1      |
| screen                     | 4.9.1            | 5.0.0       |
| seatd                      | 0.8.0            | 0.9.1       |
| shaderc                    | 2024.1           | 2024.3      |
| shadow                     | 4.16.0           | 4.17.3      |
| socat                      | 1.8.0.0          | 1.8.0.3     |
| spirv-headers              | 1.3.290.0        | 1.4.309.0   |
| spirv-tools                | 1.3.290.0        | 1.4.309.0   |
| sqlite3                    | 3.46.1           | 3.48.0      |
| strace                     | 6.10             | 6.12        |
| stress-ng                  | 0.18.02          | 0.18.11     |
| subversion                 | 1.14.3           | 1.14.5      |
| sudo                       | 1.9.15p5         | 1.9.16p2    |
| swig                       | 4.2.1            | 4.3.0       |
| sysklogd                   | 2.6.1            | 2.7.1       |
| sysstat                    | 12.7.6           | 12.7.7      |
| systemd                    | 256.5            | 257.4       |
| systemd-boot               | 256.5            | 257.4       |
| syste-<br>md-boot-native   | 256.5            | 257.4       |
| syste-<br>md-systemctl-nat | 1.0              | 257.4       |
| systemtap                  | 5.1              | 5.2         |
| system-<br>tap-native      | 5.1              | 5.2         |
| sysvinit                   | 3.04             | 3.14        |
| tcl                        | 8.6.14           | 9.0.1       |
| texinfo                    | 7.1              | 7.2         |
| tiff                       | 4.6.0            | 4.7.0       |
| ttyrun                     | 2.34.0           | 2.37.0      |
| u-boot                     | 2024.07          | 2025.01     |
| u-boot-tools               | 2024.07          | 2025.01     |
| usbutils                   | 017              | 018         |
| utfcpp                     | 4.0.5            | 4.0.6       |
| util-linux                 | 2.40.2           | 2.40.4      |
| util-linux-libu            | 2.40.2           | 2.40.4      |

continues on next page

Tabella 7 – continua dalla pagina precedente

| Recipe               | Previous version      | New version           |
|----------------------|-----------------------|-----------------------|
| util-macros          | 1.20.1                | 1.20.2                |
| vala                 | 0.56.17               | 0.56.18               |
| valgrind             | 3.23.0                | 3.24.0                |
| vim                  | 9.1.1043              | 9.1.1198              |
| vim-tiny             | 9.1.1043              | 9.1.1198              |
| virglrenderer        | 1.0.1                 | 1.1.0                 |
| vte                  | 0.76.3                | 0.78.2                |
| vulkan-headers       | 1.3.290.0             | 1.4.309.0             |
| vulkan-loader        | 1.3.290.0             | 1.4.309.0             |
| vulkan-samples       | git (fdce530c0295...) | git (8547ce1022a1...) |
| vulkan-tools         | 1.3.290.0             | 1.4.309.0             |
| vul-                 | 1.3.290.0             | 1.4.309.0             |
| kan-utility-libr     |                       |                       |
| vul-                 | 1.3.290.0             | 1.4.309.0             |
| kan-validation-l     |                       |                       |
| vulkan-volk          | 1.3.290.0             | 1.4.309.0             |
| way-                 | 1.37                  | 1.41                  |
| land-protocols       |                       |                       |
| webkitgtk            | 2.44.3                | 2.48.0                |
| weston               | 13.0.3                | 14.0.1                |
| wget                 | 1.24.5                | 1.25.0                |
| wireless-regdb       | 2024.10.07            | 2025.02.20            |
| wpebackend-fdo       | 1.14.2                | 1.16.0                |
| xauth                | 1.1.3                 | 1.1.4                 |
| xcb-util-cursor      | 0.1.4                 | 0.1.5                 |
| xf86-input-evdev     | 2.10.6                | 2.11.0                |
| xf86-input-libr      | 1.4.0                 | 1.5.0                 |
| xf86-input-synaptics | 1.9.2                 | 1.10.0                |
| xf86-video-fbdev     | 0.5.0                 | 0.5.1                 |
| xhost                | 1.0.9                 | 1.0.10                |
| xinit                | 1.4.2                 | 1.4.4                 |
| xkey-                | 2.42                  | 2.44                  |
| board-config         |                       |                       |
| xprop                | 1.2.7                 | 1.2.8                 |
| xrandr               | 1.5.2                 | 1.5.3                 |
| xtrans               | 1.5.0                 | 1.6.0                 |
| xxhash               | 0.8.2                 | 0.8.3                 |
| xz                   | 5.6.2                 | 5.6.4                 |
| zstd                 | 1.5.6                 | 1.5.7                 |

## Contributors to 5.2

Thanks to the following people who contributed to this release:

- Aditya Tayade
- Adrian Freihofer
- Alban Bedel
- Aleksandar Nikolic
- Alessio Cascone
- Alexander Hirsch
- Alexander Kanavin
- Alexander Sverdlin
- Alexander van Gessel
- Alexander Yurkov
- Alexandre Marques
- Alexis Cellier
- Alex Kiernan
- Andrej Valek
- Angelo Ribeiro
- Antonin Godard
- Archana Polampalli
- Artur Kowalski
- Awais Belal
- Balaji Pothunoori
- Bartosz Golaszewski
- Bastian Germann
- Bastian Krause
- Bastien JAUNY
- BELHADJ SALEM Talel
- Benjamin Bara
- Benjamin Grosschartner
- Benjamin Szőke
- Bin Lan
- Bruce Ashfield

- Changhyeok Bae
- Changqing Li
- Chen Qi
- Chris Laplante
- Christian Lindeberg
- Christian Taedcke
- Christos Gavros
- Claus Stovgaard
- Clayton Casciato
- Colin McAllister
- Daniel Ammann
- Daniel McGregor
- Dan McGregor
- Deepesh Varatharajan
- Deepthi Hemraj
- Denis OSTERLAND-HEIM
- Denys Dmytriienko
- Derek Straka
- Divya Chellam
- Dmitry Baryshkov
- Enrico Jörns
- Enrico Scholz
- Eric Meyers
- Esben Haabendal
- Etienne Cordonnier
- Fabio Berton
- Fabio Estevam
- Gaël PORTAY
- Georgi, Tom
- Guðni Már Gilbert
- Guénaél Muller
- Harish Sadineni



- Haseeb Ashraf
- Hiago De Franco
- Hongxu Jia
- Igor Opaniuk
- Jagadeesh Krishnanjanappa
- Jamin Lin
- Jason Schonberg
- Jean-Pierre Geslin
- Jermain Horsman
- Jesse Riemens
- Jiaying Song
- Jinfeng Wang
- João Henrique Ferreira de Freitas
- Joerg Schmidt
- Jonas Gorski
- Jon Mason
- Jörg Sommer
- Jose Quaresma
- Joshua Watt
- Julien Stephan
- Justin Bronder
- Kai Kang
- Katariina Lounento
- Katawann
- Kevin Hao
- Khem Raj
- Koen Kooi
- Lee Chee Yang
- Lei Maohui
- Lei YU
- Leon Anavi
- Louis Rannou

- Maik Otto
- Makarios Christakis
- Marc Ferland
- Marco Felsch
- Marek Vasut
- Mark Hatle
- Markus Volk
- Marta Rybczynska
- Martin Jansa
- Mathieu Dubois-Briand
- Matthias Schiffer
- Maxin John
- Michael Estner
- Michael Halstead
- Michael Nazzareno Trimarchi
- Michael Opdenacker
- Michelle Lin
- Mikko Rapeli
- Ming Liu
- Moritz Haase
- Nick Owens
- Nicolas Dechesne
- Nikolai Merinov
- Niko Mauno
- Ninette Adhikari
- Ola x Nilsson
- Oleksandr Hnatiuk
- Oliver Kästner
- Omri Sarig
- Pascal Eberhard
- Patrik Nordvall
- Paul Barker

- Pavel Zhukov
- Pedro Ferreira
- Peter Bergin
- Peter Delevoryas
- Peter Kjellerstedt
- Peter Marko
- Peter Tatrai
- Philip Lorenz
- Priyal Doshi
- Purushottam Choudhary
- Quentin Schulz
- Ralph Siemsen
- Randy MacLeod
- Ranjitsinh Rathod
- Rasmus Villemoes
- Regis Dargent
- Ricardo Salveti
- Richard Purdie
- Robert Yang
- Rohini Sangam
- Roland Hieber
- Ross Burton
- Ryan Eatmon
- Savvas Etairidis
- Sean Nyekjaer
- Sebastian Zenker
- Sergei Zhmylev
- Shunsuke Tokumoto
- Sid-Ali
- Simon A. Eugster
- Simone Weiß
- Slawomir Stepień

- Sofiane HAMAM
- Stefan Gloor
- Stefan Herbrechtsmeier
- Stefan Koch
- Stefan Mueller-Klieser
- Steve Sakoman
- Sunil Dora
- Sven Kalmbach
- Talel BELHAJSALEM
- Thomas Perrot
- Thomas Roos
- Tim Orling
- Tom Hochstein
- Trevor Gamblin
- Ulrich Ölmann
- Valeria Petrov
- Victor J. Hansen
- Victor Kamensky
- Vijay Anusuri
- Vince Chang
- Vivek Puar
- Vyacheslav Yurkov
- Walter Schweizer
- Wang Mingyu
- Weisser, Pascal
- Xiangyu Chen
- Xiaotian Wu
- Yash Shinde
- Yi Zhao
- Yoann Congal
- Yogita Urade
- Zoltán Böszörményi

## Repositories / Downloads for Yocto-5.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `walnascar`
- Tag: `yocto-5.2`
- Git Revision: `9b96fdbb0cab02f4a6180e812b02bc9d4c41b1a5`
- Release Artefact: `poky-9b96fdbb0cab02f4a6180e812b02bc9d4c41b1a5`
- sha: `2d3c0e216c7fa71a364986be6754549e2059d37581aad0a53f0f95c33fb1eeef`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2/poky-9b96fdbb0cab02f4a6180e812b02bc9d4c41b1a5.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2/poky-9b96fdbb0cab02f4a6180e812b02bc9d4c41b1a5.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `walnascar`
- Tag: `yocto-5.2`
- Git Revision: `6ec2c52b938302b894f119f701ffcf0a847eee85`
- Release Artefact: `oecore-6ec2c52b938302b894f119f701ffcf0a847eee85`
- sha: `00453354efdd9c977d559f7c0047691bb974170ce313ac9a1e6cb94108d6c648`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2/oecore-6ec2c52b938302b894f119f701ffcf0a847eee85.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2/oecore-6ec2c52b938302b894f119f701ffcf0a847eee85.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `walnascar`
- Tag: `yocto-5.2`
- Git Revision: `edce693e1b8fabd84651aa6c0888aafbcf238577`
- Release Artefact: `meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577`
- sha: `6cfed41b54f83da91a6cf201ec1c2cd4ac284f642b1268c8fa89d2335ea2bce1`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.12`

- Tag: `yocto-5.2`
- Git Revision: `5b4e20377eea8d428edf1aeb2187c18f82ca6757`
- Release Artefact: `bitbake-5b4e20377eea8d428edf1aeb2187c18f82ca6757`
- sha: `48cff22c1e61f47adce474b636ca865e7e0b62293fc5c8829d09e7f1ac5252af`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2/bitbake-5b4e20377eea8d428edf1aeb2187c18f82ca6757.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2/bitbake-5b4e20377eea8d428edf1aeb2187c18f82ca6757.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `walnascar`
- Tag: `yocto-5.2`
- Git Revision: `b8d9cf79d299b2e553e6bc962527d835206022ec`

### 17.5.3 Release notes for Yocto-5.2.1 (Walnascar)

#### Security Fixes in Yocto-5.2.1

- connman :Fix CVE-2025-32366 and CVE-2025-32743
- ffmpeg: Fix CVE-2025-22921
- go: Fix CVE-2025-22871 and CVE-2025-22873
- iputils: Fix CVE-2025-47268
- libsoup-2.4: Fix CVE-2024-52532 and CVE-2025-32911
- libxml2: Fix CVE-2025-32414 and CVE-2025-32415
- openssh: Fix CVE-2025-32728
- perl: Fix CVE-2024-56406
- qemu: Ignore CVE-2023-1386
- ruby: Fix CVE-2025-27219, CVE-2025-27220 and CVE-2025-27221
- webkitgtk: Fix CVE-2024-54551, CVE-2025-24208, CVE-2025-24209, CVE-2025-24213, CVE-2025-24216, CVE-2025-24264 and CVE-2025-30427

#### Fixes in Yocto-5.2.1

- binutils: stable 2.44 branch updates
- bluez5: add missing tools to noinst-tools package
- build-appliance-image: Update to walnascar head revision
- buildtools-tarball: Make buildtools respects host CA certificates
- buildtools-tarball: add envvars into `BB_ENV_PASSTHROUGH_ADDITIONS`

- buildtools-tarball: move setting of envvars to respective envfile
- cdrtools-native: fix booting EFI ISO live failed
- contributor-guide/submit-changes: encourage patch version changelogs
- gcc: Fix LDRD register overlap in register-indexed mode
- glibc-y2038-tests: remove glibc-y2038-tests\_2.41.bb recipe
- glibc: Add single-threaded fast path to rand()
- glibc: stable 2.41 branch update
- go: upgrade to 1.24.3
- gobject-introspection: Fix wrong *PN* used in MULTILIB\_SCRIPTS
- icu: set ac\_cv\_path\_install to ensure install tool reproducibility
- initscripts: add function log\_success\_msg/log\_failure\_msg/log\_warning\_msg
- insane.bbclass: Move test for invalid PACKAGECONFIGs to do\_recipe\_qa
- insane.bbclass: Report all invalid PACKAGECONFIGs for a recipe at once
- libxml2: upgrade to 2.13.8
- makedumpfile: upgrade to 1.7.7
- migration-guides: add release notes for 4.0.26 and 5.0.9
- module.bbclass: add KBUILD\_EXTRA\_SYMBOLS to install
- patch.py: set commituser and commitemail for addNote
- perl: upgrade to 5.40.2
- perlcross: upgrade to 1.6.2
- poky.conf: bump version for 5.2.1
- ref-manual/release-process: update releases.svg
- ref-manual/variables.rst: document *WIC\_CREATE\_EXTRA\_ARGS*
- ref-manual/variables.rst: update *ROOT\_HOME* documentation
- ref-manual: classes: uki: Fix git links
- ref-manual: kernel-fitimage.bbclass does not use *SPL\_SIGN\_KEYNAME*
- ruby: upgrade to 3.4.3
- sbom.rst: how to disable *SPDX* generation
- scripts/install-buildtools: Update to 5.2
- sphinx-lint: various fixes
- syslinux: improve isohybrid to process extra sector count for ISO 9660 image
- test-manual/intro: remove Buildbot version used

- tzdata/tzcode-native: upgrade to 2025b
- webkitgtk: Use WTF\_CPU\_UNKNOWN when building for riscv64
- webkitgtk: upgrade to 2.48.1

### **Known Issues in Yocto-5.2.1**

- N/A

### **Contributors to Yocto-5.2.1**

- Adrian Freihofer
- Aleksandar Nikolic
- Alon Bar-Lev
- Antonin Godard
- Archana Polampalli
- Changqing Li
- Deepesh Varatharajan
- Divya Chellam
- Enrico Jörns
- Guðni Már Gilbert
- Haixiao Yan
- Hongxu Jia
- Jiaying Song
- Khem Raj
- Lee Chee Yang
- Leonard Anderweit
- Madhu Marri
- Mikko Rapeli
- Peter Kjellerstedt
- Peter Marko
- Praveen Kumar
- Priyal Doshi
- Steve Sakoman
- Trevor Woerner
- Yi Zhao
- Yogita Urade



- rajmohan r

## Repositories / Downloads for Yocto-5.2.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [walnascar](#)
- Tag: [yocto-5.2.1](#)
- Git Revision: [fd9b605507a20d850a9991316cd190c1d20dc4a6](#)
- Release Artefact: [poky-fd9b605507a20d850a9991316cd190c1d20dc4a6](#)
- sha: [0234a96fc28e60e0acaae2a03118ecde76810c47e8bb259f4950492bd75fc050](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.1/poky-fd9b605507a20d850a9991316cd190c1d20dc4a6.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.1/poky-fd9b605507a20d850a9991316cd190c1d20dc4a6.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [walnascar](#)
- Tag: [yocto-5.2.1](#)
- Git Revision: [17affdaa600896282e07fb4d64cb23195673baa1](#)
- Release Artefact: [oecore-17affdaa600896282e07fb4d64cb23195673baa1](#)
- sha: [b6c3c15004fcd1efbaa26c9695202806402730dde8e41552a70140cff67c97c9](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.1/oecore-17affdaa600896282e07fb4d64cb23195673baa1.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.1/oecore-17affdaa600896282e07fb4d64cb23195673baa1.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [walnascar](#)
- Tag: [yocto-5.2.1](#)
- Git Revision: [edce693e1b8fabd84651aa6c0888aafbcf238577](#)
- Release Artefact: [meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577](#)
- sha: [6cfed41b54f83da91a6cf201ec1c2cd4ac284f642b1268c8fa89d2335ea2bce1](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.1/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.1/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>

- Branch: 2.12
- Tag: yocto-5.2.1
- Git Revision: 5b4e20377eea8d428edf1aeb2187c18f82ca6757
- Release Artefact: bitbake-5b4e20377eea8d428edf1aeb2187c18f82ca6757
- sha: 48cff22c1e61f47adce474b636ca865e7e0b62293fc5c8829d09e7f1ac5252af
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.1/bitbake-5b4e20377eea8d428edf1aeb2187c18f82ca6757.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.1/bitbake-5b4e20377eea8d428edf1aeb2187c18f82ca6757.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: walnascar
- Tag: yocto-5.2.1
- Git Revision: 6b7019c13054bf11fb16657a3fac85831352cea9

## 17.5.4 Release notes for Yocto-5.2.2 (Walnascar)

### Security Fixes in Yocto-5.2.2

- bind: Fix CVE-2025-40775
- binutils: Fix CVE-2025-1153, CVE-2025-1178, CVE-2025-1180, CVE-2025-1181, CVE-2025-1182, CVE-2025-3198 and CVE-2025-5244
- binutils: Ignore CVE-2025-1153 (fixed in current version)
- epiphany: Fix CVE-2025-3839
- go: Fix CVE-2025-0913, CVE-2025-4673 and CVE-2025-22874
- go: Ignore CVE-2024-3566
- kea: Fix CVE-2025-32801, CVE-2025-32802 and CVE-2025-32803
- libarchive: Fix CVE-2025-5914
- libsoup-2.4: Fix CVE-2024-52530, CVE-2024-52531, CVE-2025-2784, CVE-2025-4476, CVE-2025-4948, CVE-2025-4969, CVE-2025-32050, CVE-2025-32052, CVE-2025-32053, CVE-2025-32906, CVE-2025-32907, CVE-2025-32909, CVE-2025-32910, CVE-2025-32912, CVE-2025-32913, CVE-2025-32914, CVE-2025-46420 and CVE-2025-46421
- libsoup: Fix CVE-2025-4476, CVE-2025-4948, CVE-2025-4969, CVE-2025-32907, CVE-2025-32908 and CVE-2025-32914
- linux-yocto: Fix CVE-2023-3079, CVE-2023-52904, CVE-2023-52979, CVE-2025-22102, CVE-2025-37800, CVE-2025-37801, CVE-2025-37802, CVE-2025-37805, CVE-2025-37821, CVE-2025-37838, CVE-2025-37890, CVE-2025-37891, CVE-2025-37894, CVE-2025-37895, CVE-2025-37897, CVE-2025-37899, CVE-2025-37900, CVE-2025-37901, CVE-2025-37903, CVE-2025-37905, CVE-2025-37907, CVE-2025-37908, CVE-2025-37909, CVE-2025-37910, CVE-2025-37911, CVE-2025-37912,

CVE-2025-37913, CVE-2025-37914, CVE-2025-37915, CVE-2025-37916, CVE-2025-37917, CVE-2025-37918, CVE-2025-37919, CVE-2025-37920, CVE-2025-37921, CVE-2025-37922, CVE-2025-37923, CVE-2025-37924, CVE-2025-37926, CVE-2025-37927, CVE-2025-37928, CVE-2025-37929, CVE-2025-37930, CVE-2025-37931, CVE-2025-37932, CVE-2025-37933, CVE-2025-37934, CVE-2025-37935, CVE-2025-37936, CVE-2025-37946, CVE-2025-37947, CVE-2025-37948, CVE-2025-37949, CVE-2025-37951, CVE-2025-37952, CVE-2025-37953, CVE-2025-37954, CVE-2025-37955, CVE-2025-37956, CVE-2025-37957, CVE-2025-37958, CVE-2025-37959, CVE-2025-37960, CVE-2025-37961, CVE-2025-37962, CVE-2025-37963, CVE-2025-37964, CVE-2025-37965, CVE-2025-37967, CVE-2025-37968, CVE-2025-37969, CVE-2025-37970, CVE-2025-37971, CVE-2025-37972, CVE-2025-37973, CVE-2025-37974, CVE-2025-37990, CVE-2025-37991, CVE-2025-37992, CVE-2025-37993, CVE-2025-37994, CVE-2025-37995, CVE-2025-37997, CVE-2025-37998 and CVE-2025-37999

- linux-yocto: Ignore CVE-2023-3079 and CVE-2025-37996
- net-tools: Fix CVE-2025-46836
- ofono: Fix CVE-2024-7537
- python3-setuptools: Fix CVE-2025-47273
- python3-urllib3: Fix CVE-2025-50181 and CVE-2025-50182
- sqlite3: Fix CVE-2025-3277 and CVE-2025-29088
- sqlite3: mark CVE-2025-29087 as patched
- systemd: Fix CVE-2025-4598
- xz: Fix CVE-2025-31115

### Fixes in Yocto-5.2.2

- bind: upgrade to 9.20.9
- bitbake: toaster/tests/buildtest: Switch to new CDN
- brief-yoctoprojectqs/index.rst: replace removed macro
- brief-yoctoprojectqs/ref-manual: Switch to new CDN
- bsp guide: update kernel version example to 6.12
- bsp-guide: update all of section 1.8.2 to reflect current beaglebone conf file
- bsp-guide: update lonely "4.12" kernel reference to "6.12"
- build-appliance-image: Update to walnascar head revision
- cmake: Correctly handle cost data of tests with arbitrary chars in name
- conf.py: tweak SearchEnglish to be hyphen-friendly
- cve-exclusion\_6.12.inc: Update using current cvelistV5
- cve-exclusions: correct cve status for 5 entries
- docs: Clean up explanation of minimum required version numbers
- docs: README: specify how to contribute instead of pointing at another file

- docs: conf.py: silence SyntaxWarning on js\_splitter\_code
- docs: sphinx-lint: superfluous backtick in front of role
- docs: sphinx-lint: unbalanced inline literal markup
- epiphany: upgrade to 48.3
- gcc: Upgrade to GCC 14.3
- gcc: fix incorrect preprocessor line numbers in large files
- genericarm64.conf: increase *INITRAMFS\_MAXSIZE*
- ghostscript: upgrade to 10.05.1
- glibc: stable 2.41 branch updates
- go: upgrade to 1.24.4
- kea: upgrade to 2.6.3
- libarchive: upgrade to 3.7.9
- libmatchbox: upgrade to 1.14
- libsoup: upgrade to 3.6.5
- linux-yocto/6.12: bsp/genericarm64: modular configuration updates
- linux-yocto/6.12: libbpf: silence maybe-uninitialized warning from clang
- linux-yocto/6.12: update to v6.12.31
- linux-yoto/6.12: bsp/arm: fix CONFIG\_CRYPTOLIB\_CHACHA
- linux/cve-exclusion: Execute the script after changing to the new data source
- linux/cve-exclusion: correct fixed-version calculation
- linux/cve-exclusion: do not shift first\_affected
- linux/cve-exclusion: update exclusions after script fixes
- linux/cve-exclusion: update with latest cvelistV5
- linux/generate-cve-exclusions: show the name and version of the data source
- linux/generate-cve-exclusions: use data from CVEProject
- linux: cve-exclusions: Amend terminology
- linux: cve-exclusions: Fix false negatives
- local.conf.sample: Switch to new CDN
- migration-guides: add release notes for 4.0.27, 5.0.10, 5.2.1
- nfs-utils: don't use signals to shut down nfs server.
- oeqa/sstatetests: Fix *NATIVE\_LSB\_STRING* handling
- oeqa/sstatetests: Improve/fix sstate creation tests

- overview-manual: small number of pedantic cleanups
- package\_rpm.bbclass: Remove empty build directory
- poky.conf: bump version for 5.2.2
- python3-pyobject: *RDEPENDS* on gobject-introspection
- python3-requests: upgrade to 2.32.4
- python3: backport the full fix for importlib scanning invalid distributions
- python3: drop old nis module dependencies
- python3: remove obsolete deletion of non-deterministic .pyc files
- python3: upgrade to 3.13.4
- ref-manual/variables.rst: document *IMAGE\_ROOTFS\_MAXSIZE* *INHIBIT\_DEFAULT\_RUST\_DEPS*  
*INHIBIT\_UPDATERCD\_BBCLASS* *INITRAMFS\_MAXSIZE* *KERNEL\_SPLIT\_MODULES*  
*SSTATE\_SKIP\_CREATION*
- ref-manual: clarify *KCONFIG\_MODE* default behaviour
- ref-manual: classes: nativesdk: move note to appropriate section
- ref-manual: classes: reword to clarify that native/nativesdk options are exclusive
- scripts/install-buildtools: Update to 5.2.1
- sstate: apply proper umask when fetching from SSTATE\_MIRROR
- sstatetests: Switch to new CDN
- systemd.bbclass: generate preset for templates
- systemd: upgrade to 257.6
- tcf-agent: correct the *SRC\_URI*
- testimage: get real os-release file
- tune-cortexr52: Remove aarch64 for ARM Cortex-R52
- util-linux: fixagetty segfault issue
- xwayland: Add missing libtirpc dependency

### Known Issues in Yocto-5.2.2

- N/A

### Contributors to Yocto-5.2.2

- Aleksandar Nikolic
- Alper Ak
- Antonin Godard
- Archana Polampalli

- Bruce Ashfield
- Carlos Sánchez de La Lama
- Changqing Li
- Christos Gavros
- Colin Pinnell McAllister
- Daniel Turull
- Deepesh Varatharajan
- Dixit Parmar
- Enrico Jörns
- Etienne Cordonnier
- Guocai He
- Guðni Már Gilbert
- Gyorgy Sarvari
- Harish Sadineni
- Jiaying Song
- Lee Chee Yang
- Mathieu Dubois-Briand
- Mikko Rapeli
- Moritz Haase
- NeilBrown
- Niko Mauno
- Patrick Williams
- Peter Marko
- Praveen Kumar
- Quentin Schulz
- Randy MacLeod
- Rasmus Villemoes
- Richard Purdie
- Robert P. J. Day
- Robert Yang
- Ross Burton
- Sandeep Gundlupet Raju

- Steve Sakoman
- Trevor Gamblin
- Trevor Woerner
- Wang Mingyu
- Yash Shinde
- Yi Zhao
- Yogita Urade
- Yongxin Liu

## Repositories / Downloads for Yocto-5.2.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `walnascar`
- Tag: `yocto-5.2.2`
- Git Revision: `41038342a471b4a8884548568ad147a1704253a3`
- Release Artefact: `poky-41038342a471b4a8884548568ad147a1704253a3`
- sha: `4b1e9c80949e5c5ab5ffeb4fa3dad43b74b813fc9d132caabf1fc8c38bd8f5e`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.2/poky-41038342a471b4a8884548568ad147a1704253a3.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.2/poky-41038342a471b4a8884548568ad147a1704253a3.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `walnascar`
- Tag: `yocto-5.2.2`
- Git Revision: `c855be07828c9cff3aa7ddfa04eb0c4df28658e4`
- Release Artefact: `oecore-c855be07828c9cff3aa7ddfa04eb0c4df28658e4`
- sha: `c510b69b984be7ad8045236a3dde9bc4f5833bc9f3045dc04d6442a9453165f4`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.2/oecore-c855be07828c9cff3aa7ddfa04eb0c4df28658e4.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.2/oecore-c855be07828c9cff3aa7ddfa04eb0c4df28658e4.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `walnascar`
- Tag: `yocto-5.2.2`

- Git Revision: [edce693e1b8fabd84651aa6c0888aafbcf238577](#)
- Release Artefact: [meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577](#)
- sha: [6cfed41b54f83da91a6cf201ec1c2cd4ac284f642b1268c8fa89d2335ea2bce1](#)
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.2/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.2/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.12
- Tag: yocto-5.2.2
- Git Revision: [74c28e14a9b5e2ff908a03f93c189efa6f56b0ca](#)
- Release Artefact: [bitbake-74c28e14a9b5e2ff908a03f93c189efa6f56b0ca](#)
- sha: [1d417990d922289152af6274d461d7809d06c290d57e5373fd46bb0112e6b812](#)
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.2/bitbake-74c28e14a9b5e2ff908a03f93c189efa6f56b0ca.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.2/bitbake-74c28e14a9b5e2ff908a03f93c189efa6f56b0ca.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: [walnascar](#)
- Tag: yocto-5.2.2
- Git Revision: [5754fb5efb54cf06f96012a88619baba0995b0fc](#)

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [walnascar](#)
- Tag: yocto-5.2.2
- Git Revision: [85f8e5c799ef38c6dcca615d7cc6baff325df259](#)

## 17.5.5 Release notes for Yocto-5.2.3 (Walnascar)

### Security Fixes in Yocto-5.2.3

- avahi: Fix [CVE-2024-52615](#) and [CVE-2024-52616](#)
- bind: Fix [cve\\_nist:2025-40777](#)
- binutils: Fix [CVE-2025-5245](#), [CVE-2025-7545](#) and [CVE-2025-7546](#)
- busybox: Fix [CVE-2023-39810](#)
- coreutils: Fix [CVE-2025-5278](#)



- curl: Ignore CVE-2025-4947 and CVE-2025-5025
- dpkg: Fix CVE-2025-6297
- dropbear: Fix CVE-2025-47203
- gdk-pixbuf: Fix CVE-2025-7345
- git: Fix CVE-2025-27613, CVE-2025-27614, CVE-2025-46334, CVE-2025-46835, CVE-2025-48384, CVE-2025-48385 and CVE-2025-48386
- gnutls: Fix CVE-2025-6395, CVE-2025-32988, CVE-2025-32989 and CVE-2025-32990
- go: Fix CVE-2025-4674
- icu: Fix CVE-2025-5222
- iputils: Fix CVE-2025-48964
- libarchive: Fix CVE-2025-5915
- libpam: Fix CVE-2024-10963
- libsoup-2.4: Fix CVE-2025-4945
- libsoup: Fix CVE-2025-4945, CVE-2025-6021, CVE-2025-6170, CVE-2025-49794, CVE-2025-49795 and CVE-2025-49796
- linux-yocto/6.12: Ignore CVE-2021-47342, CVE-2022-49934, CVE-2022-49935, CVE-2022-49936, CVE-2022-49937, CVE-2022-49938, CVE-2022-49939, CVE-2022-49940, CVE-2022-49942, CVE-2022-49943, CVE-2022-49944, CVE-2022-49945, CVE-2022-49946, CVE-2022-49947, CVE-2022-49948, CVE-2022-49949, CVE-2022-49950, CVE-2022-49951, CVE-2022-49952, CVE-2022-49953, CVE-2022-49954, CVE-2022-49955, CVE-2022-49956, CVE-2022-49957, CVE-2022-49958, CVE-2022-49959, CVE-2022-49960, CVE-2022-49961, CVE-2022-49962, CVE-2022-49963, CVE-2022-49964, CVE-2022-49965, CVE-2022-49966, CVE-2022-49967, CVE-2022-49968, CVE-2022-49969, CVE-2022-49970, CVE-2022-49971, CVE-2022-49972, CVE-2022-49973, CVE-2022-49974, CVE-2022-49975, CVE-2022-49976, CVE-2022-49977, CVE-2022-49978, CVE-2022-49979, CVE-2022-49980, CVE-2022-49981, CVE-2022-49982, CVE-2022-49983, CVE-2022-49984, CVE-2022-49985, CVE-2022-49986, CVE-2022-49987, CVE-2022-49989, CVE-2022-49990, CVE-2022-49991, CVE-2022-49992, CVE-2022-49993, CVE-2022-49994, CVE-2022-49995, CVE-2022-49996, CVE-2022-49997, CVE-2022-49998, CVE-2022-49999, CVE-2022-50000, CVE-2022-50001, CVE-2022-50002, CVE-2022-50003, CVE-2022-50004, CVE-2022-50005, CVE-2022-50006, CVE-2022-50007, CVE-2022-50008, CVE-2022-50009, CVE-2022-50010, CVE-2022-50011, CVE-2022-50012, CVE-2022-50013, CVE-2022-50014, CVE-2022-50015, CVE-2022-50016, CVE-2022-50017, CVE-2022-50019, CVE-2022-50020, CVE-2022-50021, CVE-2022-50022, CVE-2022-50023, CVE-2022-50024, CVE-2022-50025, CVE-2022-50026, CVE-2022-50027, CVE-2022-50028, CVE-2022-50029, CVE-2022-50030, CVE-2022-50031, CVE-2022-50032, CVE-2022-50033, CVE-2022-50034, CVE-2022-50035, CVE-2022-50036, CVE-2022-50037, CVE-2022-50038, CVE-2022-50039, CVE-2022-50040, CVE-2022-50041, CVE-2022-50042, CVE-2022-50043, CVE-2022-50044, CVE-2022-50045, CVE-2022-50046, CVE-2022-50047, CVE-2022-50048, CVE-2022-50049, CVE-2022-50050, CVE-2022-50051, CVE-2022-50052, CVE-2022-50053, CVE-2022-50054, CVE-2022-50055, CVE-2022-50056, CVE-2022-50057, CVE-2022-50058, CVE-2022-50059, CVE-2022-50060, CVE-2022-50061, CVE-2022-50062, CVE-2022-50063, CVE-2022-50064, CVE-2022-50065, CVE-2022-50066, CVE-2022-50067, CVE-2022-50068, CVE-2022-50069, CVE-2022-50070, CVE-2022-50071,

CVE-2022-50072, CVE-2022-50073, CVE-2022-50074, CVE-2022-50075, CVE-2022-50076, CVE-2022-50077, CVE-2022-50078, CVE-2022-50079, CVE-2022-50080, CVE-2022-50082, CVE-2022-50083, CVE-2022-50084, CVE-2022-50085, CVE-2022-50086, CVE-2022-50087, CVE-2022-50088, CVE-2022-50089, CVE-2022-50090, CVE-2022-50091, CVE-2022-50092, CVE-2022-50093, CVE-2022-50094, CVE-2022-50095, CVE-2022-50096, CVE-2022-50097, CVE-2022-50098, CVE-2022-50099, CVE-2022-50100, CVE-2022-50101, CVE-2022-50102, CVE-2022-50103, CVE-2022-50104, CVE-2022-50105, CVE-2022-50106, CVE-2022-50107, CVE-2022-50108, CVE-2022-50109, CVE-2022-50110, CVE-2022-50111, CVE-2022-50112, CVE-2022-50113, CVE-2022-50114, CVE-2022-50115, CVE-2022-50116, CVE-2022-50117, CVE-2022-50118, CVE-2022-50119, CVE-2022-50120, CVE-2022-50121, CVE-2022-50122, CVE-2022-50123, CVE-2022-50124, CVE-2022-50125, CVE-2022-50126, CVE-2022-50127, CVE-2022-50129, CVE-2022-50130, CVE-2022-50131, CVE-2022-50132, CVE-2022-50133, CVE-2022-50134, CVE-2022-50135, CVE-2022-50136, CVE-2022-50137, CVE-2022-50138, CVE-2022-50139, CVE-2022-50140, CVE-2022-50141, CVE-2022-50142, CVE-2022-50143, CVE-2022-50144, CVE-2022-50145, CVE-2022-50146, CVE-2022-50147, CVE-2022-50148, CVE-2022-50149, CVE-2022-50151, CVE-2022-50152, CVE-2022-50153, CVE-2022-50154, CVE-2022-50155, CVE-2022-50156, CVE-2022-50157, CVE-2022-50158, CVE-2022-50159, CVE-2022-50160, CVE-2022-50161, CVE-2022-50162, CVE-2022-50163, CVE-2022-50164, CVE-2022-50165, CVE-2022-50166, CVE-2022-50167, CVE-2022-50168, CVE-2022-50169, CVE-2022-50170, CVE-2022-50171, CVE-2022-50172, CVE-2022-50173, CVE-2022-50174, CVE-2022-50175, CVE-2022-50176, CVE-2022-50177, CVE-2022-50178, CVE-2022-50179, CVE-2022-50181, CVE-2022-50182, CVE-2022-50183, CVE-2022-50184, CVE-2022-50185, CVE-2022-50186, CVE-2022-50187, CVE-2022-50188, CVE-2022-50189, CVE-2022-50190, CVE-2022-50191, CVE-2022-50192, CVE-2022-50193, CVE-2022-50194, CVE-2022-50195, CVE-2022-50196, CVE-2022-50197, CVE-2022-50198, CVE-2022-50199, CVE-2022-50200, CVE-2022-50201, CVE-2022-50202, CVE-2022-50203, CVE-2022-50204, CVE-2022-50205, CVE-2022-50206, CVE-2022-50207, CVE-2022-50208, CVE-2022-50209, CVE-2022-50210, CVE-2022-50211, CVE-2022-50212, CVE-2022-50213, CVE-2022-50214, CVE-2022-50215, CVE-2022-50217, CVE-2022-50218, CVE-2022-50219, CVE-2022-50220, CVE-2022-50221, CVE-2022-50222, CVE-2022-50223, CVE-2022-50224, CVE-2022-50225, CVE-2022-50226, CVE-2022-50227, CVE-2022-50228, CVE-2022-50229, CVE-2022-50231, CVE-2024-26710, CVE-2024-57976 and CVE-2024-58091

- **linux-yocto/6.12: (cont.) Ignore** CVE-2025-21817, CVE-2025-22101, CVE-2025-22112, CVE-2025-22119, CVE-2025-22122, CVE-2025-22123, CVE-2025-22128, CVE-2025-23137, CVE-2025-23155, CVE-2025-37842, CVE-2025-37855, CVE-2025-38000, CVE-2025-38001, CVE-2025-38002, CVE-2025-38003, CVE-2025-38004, CVE-2025-38005, CVE-2025-38006, CVE-2025-38007, CVE-2025-38008, CVE-2025-38009, CVE-2025-38010, CVE-2025-38011, CVE-2025-38012, CVE-2025-38013, CVE-2025-38014, CVE-2025-38015, CVE-2025-38016, CVE-2025-38017, CVE-2025-38018, CVE-2025-38019, CVE-2025-38020, CVE-2025-38021, CVE-2025-38022, CVE-2025-38023, CVE-2025-38024, CVE-2025-38025, CVE-2025-38027, CVE-2025-38028, CVE-2025-38031, CVE-2025-38032, CVE-2025-38033, CVE-2025-38034, CVE-2025-38035, CVE-2025-38037, CVE-2025-38038, CVE-2025-38039, CVE-2025-38040, CVE-2025-38043, CVE-2025-38044, CVE-2025-38045, CVE-2025-38047, CVE-2025-38048, CVE-2025-38050, CVE-2025-38051, CVE-2025-38052, CVE-2025-38053, CVE-2025-38054, CVE-2025-38055, CVE-2025-38056, CVE-2025-38057, CVE-2025-38058, CVE-2025-38059, CVE-2025-38060, CVE-2025-38061, CVE-2025-38062, CVE-2025-38063, CVE-2025-38065, CVE-2025-38066, CVE-2025-38068, CVE-2025-38069, CVE-2025-38070, CVE-2025-38071, CVE-2025-38072, CVE-2025-38073, CVE-2025-38074, CVE-2025-38075, CVE-2025-38076, CVE-2025-38077, CVE-2025-38078, CVE-2025-38079,

## 17.5. Release 5.2 (walnascar) 1227

- ncurses: Fix [CVE-2025-6141](#)
- python3: Fix [CVE-2025-8194](#)
- sqlite3: Fix [CVE-2025-6965](#)
- sudo: Fix [CVE-2025-32462](#) and [CVE-2025-32463](#)
- webkitgtk: Fix [CVE-2025-24223](#), [CVE-2025-31204](#), [CVE-2025-31205](#), [CVE-2025-31206](#), [CVE-2025-31215](#) and [CVE-2025-31257](#)
- xserver-xorg: Fix [CVE-2025-49175](#), [CVE-2025-49176](#), [CVE-2025-49177](#), [CVE-2025-49178](#), [CVE-2025-49179](#) and [CVE-2025-49180](#)

### Fixes in Yocto-5.2.3

- bind: upgrade to 9.20.11
- binutils: stable 2.44 branch updates
- bitbake: test/fetch: Switch u-boot based test to use our own mirror
- bitbake: utils: Optimise signal/sigmask performance
- build-appliance-image: Update to walnascar head revision
- ca-certificates: correct the *SRC\_URI*
- conf.py: improve SearchEnglish to handle terms with dots
- dev-manual/start.rst: added missing command in Optimize your VHDX file using DiskPart
- dev-manual/start.rst: mention that *PERSISTENT\_DIR* should be shared too
- dev-manual/start.rst: remove basic setup for hash equivalence
- dev-manual/start.rst: remove shared *PERSISTENT\_DIR* mentions
- docs/variables.rst: remove references to obsolete tar packaging
- git: upgrade to 2.49.1
- glibc: stable 2.41 branch updates
- gnutls: upgrade to 3.8.10
- go: upgrade to 1.24.5
- kea: set correct permissions for /var/run/kea
- libpam: upgrade to 1.7.1
- linux-yocto/6.12: riscv tune fragments
- linux-yocto/6.12: riscv: Enable *TUNE\_FEATURES* based *KERNEL\_FEATURES*
- linux-yocto/6.12: update to v6.12.38
- linux-yocto/6.12: yaffs2: silence warnings
- ltp: Skip semctl08 when *\_\_USE\_TIME64\_REDIRECTS* is defined
- ltp: backport patch to fix compilation error for Skylake -march=x86-64-v3

- migration-guides: add release notes for 4.0.28, 5.0.11, 5.2.2
- mingetty: fix do\_package warning
- mtools: upgrade to 4.0.49
- openssl: upgrade to 3.4.2
- orc: set *CVE\_PRODUCT*
- overview-manual/concepts.rst: fix sayhello hardcoded bindir
- overview-manual/concepts.rst: mention *PERSISTENT\_DIR* for user configuration
- overview-manual/yp-intro.rst: fix broken link to article
- poky.conf: bump version for 5.2.3
- poky.yaml.in: increase minimum RAM from 8 to 32
- python3: update CVE product
- ref-manual/classes.rst: document the testexport class
- ref-manual/classes.rst: drop obsolete QA errors
- ref-manual/classes.rst: insane: drop cve\_status\_not\_in\_db
- ref-manual/structure.rst: remove shared *PERSISTENT\_DIR* mentions
- ref-manual/structure.rst: update with info on *PERSISTENT\_DIR*
- ref-manual/system-requirements.rst: update supported distributions
- ref-manual/variables.rst: document *SPL\_DTB\_BINARY*
- ref-manual/variables.rst: document the *FIT\_CONF\_PREFIX* variable
- ruby-ptest: some ptest fixes
- ruby: upgrade to 3.4.4
- rust: Fix malformed hunk header in rustix patch
- scripts/install-buildtools: Update to 5.2.2
- sudo: upgrade to 1.9.17p1
- test-manual/understand-autobuilder.rst: mention hashequiv server
- webkitgtk: Fix build break on non-arm/non-x86 systems
- webkitgtk: Use gcc to compile for arm target
- webkitgtk: upgrade to 2.48.2
- xserver-xorg: upgrade to 21.1.18

### **Known Issues in Yocto-5.2.3**

- N/A

### **Contributors to Yocto-5.2.3**

- Aleksandar Nikolic
- Antonin Godard
- Archana Polampalli
- Bruce Ashfield
- Changqing Li
- Chen Qi
- Deepesh Varatharajan
- Divya Chellam
- Enrico Jörns
- Erik Lindsten
- Gyorgy Sarvari
- Hongxu Jia
- Jiaying Song
- Jinfeng Wang
- Khem Raj
- Lee Chee Yang
- Marco Cavallini
- Mark Hatle
- Peter Marko
- Praveen Kumar
- Richard Purdie
- Robert P. J. Day
- Steve Sakoman
- Vijay Anusuri
- Wang Mingyu
- Yash Shinde
- Yi Zhao
- Yogesh Tyagi
- Yogita Urade

- Zhang Peng

## Repositories / Downloads for Yocto-5.2.3

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [walnascar](#)
- Tag: [yocto-5.2.3](#)
- Git Revision: [db04028d9070f05c3b5dee728473fb234bd24f05](#)
- Release Artefact: [poky-db04028d9070f05c3b5dee728473fb234bd24f05](#)
- sha: [32e1d457d5de0041ee423727b5690fbde58c485a42b8ed81ecebb7bb2d8c58cc](#)
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.3/poky-db04028d9070f05c3b5dee728473fb234bd24f05.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.3/poky-db04028d9070f05c3b5dee728473fb234bd24f05.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [walnascar](#)
- Tag: [yocto-5.2.3](#)
- Git Revision: [347cb0861dde58613541ce692778f907943a60ea](#)
- Release Artefact: [oecore-347cb0861dde58613541ce692778f907943a60ea](#)
- sha: [88cbb79f7bc2de9d931cfa1092463005189972d4584cdae1562621df79f09fbd](#)
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.3/oecore-347cb0861dde58613541ce692778f907943a60ea.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.3/oecore-347cb0861dde58613541ce692778f907943a60ea.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [walnascar](#)
- Tag: [yocto-5.2.3](#)
- Git Revision: [edce693e1b8fabd84651aa6c0888aafbcf238577](#)
- Release Artefact: [meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577](#)
- sha: [6cfed41b54f83da91a6cf201ec1c2cd4ac284f642b1268c8fa89d2335ea2bce1](#)
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.3/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.3/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>

- Branch: 2.12
- Tag: yocto-5.2.3
- Git Revision: 710f98844ae30416bdf6a01b655df398b49574ec
- Release Artefact: bitbake-710f98844ae30416bdf6a01b655df398b49574ec
- sha: e30aa4739e3104634184b1dd7d5502f0994a725daec15929c4adf1164aa1296d
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.3/bitbake-710f98844ae30416bdf6a01b655df398b49574ec.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.3/bitbake-710f98844ae30416bdf6a01b655df398b49574ec.tar.bz2>

meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: walnascar
- Tag: yocto-5.2.3
- Git Revision: ce011415ab4e583a4545cd91aceff4190225f31d

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: walnascar
- Tag: yocto-5.2.3
- Git Revision: e664a70adb5bc19041b3b5f553fb90dcddff99d0

## 17.5.6 Release notes for Yocto-5.2.4 (Walnascar)

### Security Fixes in Yocto-5.2.4

- binutils: Fix CVE-2025-8225
- binutils: Ignore CVE-2025-8224
- cups: Fix CVE-2025-58060 and CVE-2025-58364
- curl: Fix CVE-2025-9086 and CVE-2025-10148
- elfutils: Fix CVE-2025-1352, CVE-2025-1365, CVE-2025-1371, CVE-2025-1372, CVE-2025-1376 and CVE-2025-1377
- expat: Fix CVE-2025-59375
- ffmpeg: Fix CVE-2025-7700
- glib-2.0: Fix CVE-2025-4056, CVE-2025-6052 and CVE-2025-7039
- gnutls: Ignore CVE-2025-32989 and CVE-2025-32990
- grub2: Fix CVE-2024-56738
- grub2: Ignore CVE-2024-2312



- gstreamer1.0: Ignore CVE-2025-2759, CVE-2025-3887, CVE-2025-47183, CVE-2025-47219, CVE-2025-47806, CVE-2025-47807 and CVE-2025-47808
- libarchive: Fix CVE-2025-5916, CVE-2025-5917 and CVE-2025-5918
- libpre2: Fix CVE-2025-58050
- linux-yocto/6.12: Ignore CVE-2022-50233, CVE-2023-3865, CVE-2023-3866, CVE-2023-3867, CVE-2023-4130, CVE-2023-4515, CVE-2023-32246, CVE-2023-32249, CVE-2024-58238, CVE-2024-58239, CVE-2024-58240, CVE-2025-21884, CVE-2025-22103, CVE-2025-22113, CVE-2025-22115, CVE-2025-22124, CVE-2025-22125, CVE-2025-23133, CVE-2025-37925, CVE-2025-37984, CVE-2025-38067, CVE-2025-38104, CVE-2025-38272, CVE-2025-38306, CVE-2025-38335, CVE-2025-38349, CVE-2025-38350, CVE-2025-38351, CVE-2025-38352, CVE-2025-38353, CVE-2025-38354, CVE-2025-38355, CVE-2025-38356, CVE-2025-38357, CVE-2025-38358, CVE-2025-38360, CVE-2025-38361, CVE-2025-38362, CVE-2025-38363, CVE-2025-38364, CVE-2025-38365, CVE-2025-38366, CVE-2025-38367, CVE-2025-38368, CVE-2025-38369, CVE-2025-38370, CVE-2025-38371, CVE-2025-38372, CVE-2025-38373, CVE-2025-38374, CVE-2025-38375, CVE-2025-38376, CVE-2025-38377, CVE-2025-38378, CVE-2025-38379, CVE-2025-38380, CVE-2025-38381, CVE-2025-38382, CVE-2025-38383, CVE-2025-38384, CVE-2025-38385, CVE-2025-38386, CVE-2025-38387, CVE-2025-38388, CVE-2025-38389, CVE-2025-38390, CVE-2025-38391, CVE-2025-38392, CVE-2025-38393, CVE-2025-38394, CVE-2025-38395, CVE-2025-38396, CVE-2025-38397, CVE-2025-38398, CVE-2025-38399, CVE-2025-38400, CVE-2025-38401, CVE-2025-38402, CVE-2025-38403, CVE-2025-38404, CVE-2025-38405, CVE-2025-38406, CVE-2025-38407, CVE-2025-38408, CVE-2025-38409, CVE-2025-38410, CVE-2025-38411, CVE-2025-38412, CVE-2025-38413, CVE-2025-38414, CVE-2025-38415, CVE-2025-38416, CVE-2025-38417, CVE-2025-38418, CVE-2025-38419, CVE-2025-38420, CVE-2025-38421, CVE-2025-38422, CVE-2025-38423, CVE-2025-38424, CVE-2025-38425, CVE-2025-38427, CVE-2025-38428, CVE-2025-38429, CVE-2025-38430, CVE-2025-38431, CVE-2025-38432, CVE-2025-38433, CVE-2025-38434, CVE-2025-38435, CVE-2025-38436, CVE-2025-38437, CVE-2025-38438, CVE-2025-38439, CVE-2025-38440, CVE-2025-38441, CVE-2025-38442, CVE-2025-38443, CVE-2025-38444, CVE-2025-38445, CVE-2025-38446, CVE-2025-38447, CVE-2025-38448, CVE-2025-38449, CVE-2025-38450, CVE-2025-38451, CVE-2025-38452, CVE-2025-38453, CVE-2025-38454, CVE-2025-38455, CVE-2025-38456, CVE-2025-38457, CVE-2025-38458, CVE-2025-38459, CVE-2025-38460, CVE-2025-38461, CVE-2025-38462, CVE-2025-38463, CVE-2025-38464, CVE-2025-38465, CVE-2025-38466, CVE-2025-38467, CVE-2025-38468, CVE-2025-38469, CVE-2025-38470, CVE-2025-38471, CVE-2025-38472, CVE-2025-38473, CVE-2025-38474, CVE-2025-38475, CVE-2025-38476, CVE-2025-38477, CVE-2025-38478, CVE-2025-38480, CVE-2025-38481, CVE-2025-38482, CVE-2025-38483, CVE-2025-38484, CVE-2025-38485, CVE-2025-38486, CVE-2025-38487, CVE-2025-38488, CVE-2025-38489, CVE-2025-38490, CVE-2025-38491, CVE-2025-38492, CVE-2025-38493, CVE-2025-38494, CVE-2025-38495, CVE-2025-38496, CVE-2025-38497, CVE-2025-38498, CVE-2025-38499, CVE-2025-38500, CVE-2025-38501, CVE-2025-38502, CVE-2025-38503, CVE-2025-38504, CVE-2025-38505, CVE-2025-38506, CVE-2025-38507, CVE-2025-38508, CVE-2025-38509, CVE-2025-38510, CVE-2025-38511, CVE-2025-38512, CVE-2025-38513, CVE-2025-38514, CVE-2025-38515, CVE-2025-38516, CVE-2025-38517, CVE-2025-38518, CVE-2025-38519, CVE-2025-38520, CVE-2025-38521, CVE-2025-38522, CVE-2025-38523, CVE-2025-38524, CVE-2025-38525, CVE-2025-38526, CVE-2025-38527, CVE-2025-38528, CVE-2025-38529, CVE-2025-38530, CVE-2025-38531, CVE-2025-38532, CVE-2025-38533, CVE-2025-38534, CVE-2025-38535, CVE-2025-38536, CVE-2025-38537, CVE-2025-38538, CVE-2025-38539, CVE-2025-38540, CVE-2025-38541, CVE-2025-38542, CVE-2025-38543, CVE-2025-38544, CVE-2025-

38545, CVE-2025-38546, CVE-2025-38547, CVE-2025-38548, CVE-2025-38549, CVE-2025-38550, CVE-2025-38551, CVE-2025-38552, CVE-2025-38553, CVE-2025-38554, CVE-2025-38555, CVE-2025-38556, CVE-2025-38557, CVE-2025-38558, CVE-2025-38559, CVE-2025-38560, CVE-2025-38561, CVE-2025-38562, CVE-2025-38563, CVE-2025-38564, CVE-2025-38565, CVE-2025-38566, CVE-2025-38567, CVE-2025-38568, CVE-2025-38569, CVE-2025-38570, CVE-2025-38571, CVE-2025-38572, CVE-2025-38573, CVE-2025-38574, CVE-2025-38576, CVE-2025-38577, CVE-2025-38578, CVE-2025-38579, CVE-2025-38580, CVE-2025-38581, CVE-2025-38582, CVE-2025-38583, CVE-2025-38585, CVE-2025-38586, CVE-2025-38587, CVE-2025-38588, CVE-2025-38589, CVE-2025-38590, CVE-2025-38592, CVE-2025-38593, CVE-2025-38594, CVE-2025-38595, CVE-2025-38596, CVE-2025-38598 and CVE-2025-38599

- **linux-yocto/6.12:** Ignore CVE-2025-38600, CVE-2025-38601, CVE-2025-38602, CVE-2025-38603, CVE-2025-38604, CVE-2025-38606, CVE-2025-38607, CVE-2025-38608, CVE-2025-38609, CVE-2025-38610, CVE-2025-38611, CVE-2025-38612, CVE-2025-38613, CVE-2025-38614, CVE-2025-38615, CVE-2025-38616, CVE-2025-38617, CVE-2025-38618, CVE-2025-38619, CVE-2025-38620, CVE-2025-38622, CVE-2025-38623, CVE-2025-38624, CVE-2025-38625, CVE-2025-38626, CVE-2025-38628, CVE-2025-38629, CVE-2025-38630, CVE-2025-38631, CVE-2025-38632, CVE-2025-38633, CVE-2025-38634, CVE-2025-38635, CVE-2025-38638, CVE-2025-38639, CVE-2025-38640, CVE-2025-38641, CVE-2025-38642, CVE-2025-38644, CVE-2025-38645, CVE-2025-38646, CVE-2025-38647, CVE-2025-38648, CVE-2025-38649, CVE-2025-38650, CVE-2025-38651, CVE-2025-38652, CVE-2025-38653, CVE-2025-38654, CVE-2025-38655, CVE-2025-38657, CVE-2025-38658, CVE-2025-38659, CVE-2025-38660, CVE-2025-38661, CVE-2025-38662, CVE-2025-38663, CVE-2025-38664, CVE-2025-38665, CVE-2025-38666, CVE-2025-38667, CVE-2025-38668, CVE-2025-38669, CVE-2025-38670, CVE-2025-38671, CVE-2025-38672, CVE-2025-38673, CVE-2025-38674, CVE-2025-38675, CVE-2025-38676, CVE-2025-38677, CVE-2025-38679, CVE-2025-38680, CVE-2025-38681, CVE-2025-38682, CVE-2025-38683, CVE-2025-38684, CVE-2025-38685, CVE-2025-38686, CVE-2025-38687, CVE-2025-38688, CVE-2025-38689, CVE-2025-38690, CVE-2025-38691, CVE-2025-38692, CVE-2025-38693, CVE-2025-38694, CVE-2025-38695, CVE-2025-38696, CVE-2025-38697, CVE-2025-38698, CVE-2025-38699, CVE-2025-38700, CVE-2025-38701, CVE-2025-38702, CVE-2025-38703, CVE-2025-38704, CVE-2025-38705, CVE-2025-38706, CVE-2025-38707, CVE-2025-38708, CVE-2025-38709, CVE-2025-38710, CVE-2025-38711, CVE-2025-38712, CVE-2025-38713, CVE-2025-38714, CVE-2025-38715, CVE-2025-38716, CVE-2025-38717, CVE-2025-38718, CVE-2025-38719, CVE-2025-38720, CVE-2025-38721, CVE-2025-38722, CVE-2025-38723, CVE-2025-38724, CVE-2025-38725, CVE-2025-38726, CVE-2025-38727, CVE-2025-38728, CVE-2025-38729, CVE-2025-38730, CVE-2025-38731, CVE-2025-38732, CVE-2025-38733, CVE-2025-38734, CVE-2025-38735, CVE-2025-38736, CVE-2025-38737, CVE-2025-39673, CVE-2025-39674, CVE-2025-39675, CVE-2025-39676, CVE-2025-39679, CVE-2025-39680, CVE-2025-39681, CVE-2025-39682, CVE-2025-39683, CVE-2025-39684, CVE-2025-39685, CVE-2025-39686, CVE-2025-39687, CVE-2025-39689, CVE-2025-39690, CVE-2025-39691, CVE-2025-39692, CVE-2025-39693, CVE-2025-39694, CVE-2025-39695, CVE-2025-39696, CVE-2025-39697, CVE-2025-39698, CVE-2025-39699, CVE-2025-39700, CVE-2025-39701, CVE-2025-39702, CVE-2025-39703, CVE-2025-39704, CVE-2025-39705, CVE-2025-39706, CVE-2025-39707, CVE-2025-39708, CVE-2025-39709, CVE-2025-39710, CVE-2025-39711, CVE-2025-39712, CVE-2025-39713, CVE-2025-39714, CVE-2025-39715, CVE-2025-39716, CVE-2025-39717, CVE-2025-39718, CVE-2025-39719, CVE-2025-39720, CVE-2025-39721, CVE-2025-39722, CVE-2025-39723, CVE-2025-39724, CVE-2025-39725, CVE-2025-39726, CVE-2025-39727, CVE-2025-39729, CVE-2025-39730, CVE-2025-39731, CVE-2025-

39732, CVE-2025-39733, CVE-2025-39734, CVE-2025-39736, CVE-2025-39737, CVE-2025-39738, CVE-2025-39739, CVE-2025-39740, CVE-2025-39741, CVE-2025-39742, CVE-2025-39743, CVE-2025-39744, CVE-2025-39746, CVE-2025-39747, CVE-2025-39748, CVE-2025-39749, CVE-2025-39750, CVE-2025-39751, CVE-2025-39752, CVE-2025-39753, CVE-2025-39754, CVE-2025-39756, CVE-2025-39757, CVE-2025-39758, CVE-2025-39759, CVE-2025-39760, CVE-2025-39761, CVE-2025-39763, CVE-2025-39765, CVE-2025-39766, CVE-2025-39767, CVE-2025-39768, CVE-2025-39769, CVE-2025-39770, CVE-2025-39771, CVE-2025-39772, CVE-2025-39773, CVE-2025-39774, CVE-2025-39775, CVE-2025-39776, CVE-2025-39777, CVE-2025-39779, CVE-2025-39780, CVE-2025-39781, CVE-2025-39782, CVE-2025-39783, CVE-2025-39784, CVE-2025-39785, CVE-2025-39786, CVE-2025-39787, CVE-2025-39788, CVE-2025-39790, CVE-2025-39791, CVE-2025-39792, CVE-2025-39793, CVE-2025-39794, CVE-2025-39795, CVE-2025-39796, CVE-2025-39797, CVE-2025-39798 and CVE-2025-39799

- libxslt: Fix CVE-2025-7424
- pulseaudio: Ignore CVE-2024-11586
- tiff: Fix CVE-2024-13978, CVE-2025-8176, CVE-2025-8177, CVE-2025-8534, CVE-2025-8961 and CVE-2025-9165
- tiff: Ignore CVE-2025-8851
- vim: Fix CVE-2025-53905, CVE-2025-53906, CVE-2025-55157 and CVE-2025-55158

#### Fixes in Yocto-5.2.4

- bash: use -std=gnu17 also for native *CFLAGS*
- binutils: Fix gprofng broken symbolic link with gp-\*
- bitbake: Use a "fork" multiprocessing context
- bitbake: bitbake: Bump version to 2.12.1
- bitbake: tests/fetch: Update tests after bitbake tag removal
- build-appliance-image: Update to walnascar head revision
- buildtools-tarball: fix unbound variable issues under 'set -u'
- cve-update-db-native: Fix fetcher for CVEs missing nodes
- default-distrovars.inc: Fix CONNECTIVITY\_CHECK\_URIS redirect issue
- dev-manual/security-subjects.rst: update mailing lists
- expat: upgrade to 2.7.2
- ffmpeg: upgrade to 7.1.2
- glib-2.0: update to 2.84.4
- go: upgrade 1.24.6
- gst-devtools: upgrade 1.24.13
- gstreamer1.0-libav: upgrade 1.24.13
- gstreamer1.0-plugins-bad: upgrade 1.24.13

- gstreamer1.0-plugins-base: upgrade 1.24.13
- gstreamer1.0-plugins-good: upgrade 1.24.13
- gstreamer1.0-plugins-ugly: upgrade 1.24.13
- gstreamer1.0-python: upgrade 1.24.13
- gstreamer1.0-rtsp-server: upgrade 1.24.13
- gstreamer1.0-vaapi: upgrade 1.24.13
- gstreamer1.0: upgrade 1.24.13
- lib/oe/utis: use multiprocessing from bb
- libpcr2: upgrade 10.46
- license.py: avoid deprecated ast.Str
- linux-firmware: fix *FILES* to drop *RDEPENDS* on full package
- linux-yocto/6.12: Revert "linux-yocto/6.12: riscv: Enable *TUNE\_FEATURES* based KERNEL\_FEATURES"
- linux-yocto/6.12: update to 6.12.47
- migration-guides: add release notes for 4.0.29, 5.0.12 and 5.2.3
- pkgconfig: fix build with gcc-15
- poky.conf: bump version for 5.2.4
- pulseaudio: Add audio group explicitly
- python3-setuptools: restore build\_scripts.executable support
- ref-manual/variables.rst: expand *IMAGE\_OVERHEAD\_FACTOR* glossary entry
- rpm: correct tool path in macros for no usrmerge
- rpm: keep leading '/' from sed operation
- runqemu: fix special characters bug
- rust-target-config: Add has-thread-local option
- sanity.conf: Update minimum bitbake version to 2.12.1
- sdk: The main in the C example should return an int
- systemd-systemctl-native: Install systemd-sysv-install
- systemd-systemctl-native: Use += instead of :append
- systemd.bbclass: Make systemd\_postinst run as intended
- vim: upgrade 9.1.1652
- vulnerabilities: update nvdcve file name
- yocto-uninative: Update to 4.9 for glibc 2.42 and GCC 15.1

### Known Issues in Yocto-5.2.4

- N/A

### Contributors to Yocto-5.2.4

- Antonin Godard
- Archana Polampalli
- Bruce Ashfield
- Deepak Rathore
- Haixiao Yan
- Harish Sadineni
- Hongxu Jia
- Jan Vermaete
- Joao Marcos Costa
- Joshua Watt
- Kyungjik Min
- Lee Chee Yang
- Libo Chen
- Markus Kurz
- Markus Volk
- Martin Jansa
- Mathieu Dubois-Briand
- Michael Halstead
- Patryk Seregiet
- Per x Johansson
- Peter Kjellerstedt
- Peter Marko
- Praveen Kumar
- Ross Burton
- Siddharth Doshi
- Soumya Sambu
- Steve Sakoman
- Yi Zhao
- Yogita Urade

## Repositories / Downloads for Yocto-5.2.4

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `walnascar`
- Tag: `yocto-5.2.4`
- Git Revision: `d0b46a6624ec9c61c47270745dd0b2d5abbe6ac1`
- Release Artefact: `poky-d0b46a6624ec9c61c47270745dd0b2d5abbe6ac1`
- sha: `b5fa58650f7069c1c001f48aa8eeb12ab78b5f50a414de46df1a196fdc3be8cb`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.4/poky-d0b46a6624ec9c61c47270745dd0b2d5abbe6ac1.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.4/poky-d0b46a6624ec9c61c47270745dd0b2d5abbe6ac1.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `walnascar`
- Tag: `yocto-5.2.4`
- Git Revision: `ff1c54df4e7b15df2e2c9fced59d9ad3e92ed565`
- Release Artefact: `oecore-ff1c54df4e7b15df2e2c9fced59d9ad3e92ed565`
- sha: `a348eb7c759cc02c1415d2b506903ac1d5530708c9b47550a4ae8c8d86c75728`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.4/oecore-ff1c54df4e7b15df2e2c9fced59d9ad3e92ed565.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.4/oecore-ff1c54df4e7b15df2e2c9fced59d9ad3e92ed565.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `walnascar`
- Tag: `yocto-5.2.4`
- Git Revision: `edce693e1b8fabd84651aa6c0888aafbcf238577`
- Release Artefact: `meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577`
- sha: `6cfed41b54f83da91a6cf201ec1c2cd4ac284f642b1268c8fa89d2335ea2bce1`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.4/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.4/meta-mingw-edce693e1b8fabd84651aa6c0888aafbcf238577.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.12`

- Tag: `yocto-5.2.4`
- Git Revision: `ac097300921590ed6a814f2c3fa08a59f4ded92d`
- Release Artefact: `bitbake-ac097300921590ed6a814f2c3fa08a59f4ded92d`
- sha: `ad8afd956f5378691172317c95bdd1c098d6144a7269975d7d3230707305e88a`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.2.4/bitbake-ac097300921590ed6a814f2c3fa08a59f4ded92d.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.2.4/bitbake-ac097300921590ed6a814f2c3fa08a59f4ded92d.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `walnascar`
- Tag: `yocto-5.2.4`
- Git Revision: `0993c45a1f78f302fd40c78a2a1f709daa7a0ae0`

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `walnascar`
- Tag: `yocto-5.2.4`
- Git Revision: `29330751c8a2b82b4bd80659d2a0a8bac51afca5`

## 17.6 Release 5.1 (styhead)

### 17.6.1 Release 5.1 (styhead)

#### Migration notes for 5.1 (styhead)

This section provides migration information for moving to the Yocto Project 5.1 Release (codename "styhead") from the prior release.

#### *WORKDIR* changes

##### **S = `${WORKDIR}` no longer supported**

If a recipe has *S* set to be *WORKDIR*, this is no longer supported, and an error will be issued. The recipe should be changed to:

```
S = "${UNPACKDIR}"
```

Any *WORKDIR* references where files from *SRC\_URI* are referenced should be changed to *S*. These are commonly in *do\_configure*, *do\_compile*, *do\_install* and *LIC\_FILES\_CHKSUM*.

## WORKDIR references in recipes

*WORKDIR* references in other recipes need auditing. If they reference files from *SRC\_URI*, they likely need changing to *UNPACKDIR*. These are commonly in *do\_compile* and *do\_install* for things like service or configuration files. One unusual case is `${WORKDIR}/${BP}` which should probably be set to `${S}`.

References to `../` in *LIC\_FILES\_CHKSUM* or elsewhere may need changing to *UNPACKDIR*. References to *WORKDIR* in `sed` commands are usually left as they are.

## General notes

Files from *do\_unpack* now unpack to `WORKDIR/sources-unpack/` rather than `WORKDIR/`.

If *S* is set to a subdirectory under *WORKDIR* and that subdirectory exists in `sources-unpack` after *do\_unpack* runs, it is moved to *WORKDIR*. This means that `S = "${WORKDIR}/${BP}"`, `S = "${WORKDIR}/git"` and also deeper paths continue to work as expected without changes. We cannot use symlinks to do this as it breaks autotools based recipes. Keeping all sources under `sources-unpack` wasn't considered as it meant more invasive recipes changes. The key objective was separating the *do\_unpack* task output from *WORKDIR*.

Previously, *S* was always created but after the recent changes it is no longer the case. This means the check in `do_unpack_qa` triggers where *S* is not created by a recipe while it didn't happen before. This can require to add an *S* definition to a recipe that only uses `file:// SRC_URI` entries. To be consistent, the following pattern is recommended:

```
S = "${UNPACKDIR}"
```

Building C files from *UNPACKDIR* without setting *S* to point at it does not work as the debug prefix mapping doesn't handle that.

`devtool` and `recipetool` have been updated to handle this and their support for `S = WORKDIR` and `oe-local-files` has been removed.

## Supported kernel versions

The *OLDEST\_KERNEL* setting is still "5.15" in this release, meaning that out the box, older kernels are not supported. See *4.3 migration notes* for details.

## Supported distributions

Compared to the previous releases, running BitBake is supported on new GNU/Linux distributions:

- Ubuntu 24.10
- Fedora 40
- OpenSUSE Leap 15.5
- OpenSUSE Leap 15.6

On the other hand, some earlier distributions are no longer supported:

- Ubuntu 23.04

See *all supported distributions*.



## Go language changes

- After dropping the custom *do\_unpack* from the *go* class, go recipes should now add `destsuffix=${GO_SRCURI_DESTSUFFIX}` to their *SRC\_URI* to extract them in the appropriate path. An example would be:

```
SRC_URI = "git://go.google.com/example;branch=master;protocol=https;
↪destsuffix=${GO_SRCURI_DESTSUFFIX}"
```

- Go modules are no longer compiled with `--linkmode=external`.

## systemd changes

- New *PACKAGECONFIG* value `bpf-framework` used to pre-compile eBPFs that are required for the `systemd.resource-control` features `RestrictFileSystems` and `RestrictNetworkInterfaces`.

## Recipe changes

- `gobject-introspection`: the `giscanner` utility is now shipped as a separate package in `gobject-introspection-tools`.
- `perf` no longer uses `libnewt` for compiling its TUI.
- `openssl`: do not build the test suite unless `ptest`s are enabled.

## Removed variables

The following variables have been removed:

- `TCLIBCAPPEND` is now removed as sharing *TMPDIR* for multiple `libc` providers has been supported for years.
- `VOLATILE_LOG_DIR`: *FILESYSTEM\_PERMS\_TABLES* is now used instead. By default, *FILESYSTEM\_PERMS\_TABLES* now contains the value `files/fs-perms-volatile-log.txt`, which means that volatile log is enabled. Users can disable the volatile log by removing the value `files/fs-perms-volatile-log.txt` from *FILESYSTEM\_PERMS\_TABLES*.
- `VOLATILE_TMP_DIR`: *FILESYSTEM\_PERMS\_TABLES* is now used instead. By default, *FILESYSTEM\_PERMS\_TABLES* now contains the value `files/fs-perms-volatile-tmp.txt`, which means that volatile tmp is enabled. Users can disable the volatile tmp by removing the value `files/fs-perms-volatile-tmp.txt` from *FILESYSTEM\_PERMS\_TABLES*.

## Removed recipes

The following recipes have been removed in this release:

- `liba52`: superseded by `ffmpeg`
- `libomxil`: recipe removed as its only consumer, the `gststreamer omx plugin`, was removed and has not been developed for several years
- `libnewt`: moved to `meta-oe`
- `mpeg2dec`: inactive for 10 years and superseded by `ffmpeg`

- `pytest-runner`: moved to meta-python
- `python3-importlib-metadata`: moved to meta-python
- `python3-pathlib2`: moved to meta-python
- `python3-py`: moved to meta-python
- `python3-rfc3986-validator`: moved to meta-python
- `python3-toml`: moved to meta-python
- `python3-tomli`: moved to meta-python
- `usbinit`: recipe was poorly named as it is a gadget Ethernet driver. Gadget Ethernet is of questionable use now and `usbinit` isn't referenced/used anywhere within OE-Core.

## Removed classes

The following classes have been removed in this release:

- `siteconfig`: removed as it was only used by `ncurses` and `zlib` and adding minimal added-value for a considerable amount of added runtime.

## Miscellaneous changes

- *oe-selftest* now only rewrites environment variable paths that absolutely point to `builddir` (i.e `X=$BUILDDIR/conf/` is still rewritten to point to the *oe-selftest* `conf/` directory but not `Y=$BUILDDIR/../../bitbake/` which still point to the `bitbake/` directory)

For example (taken from `autobuilder` environment): `BB_LOGCONFIG` is set as: `BB_LOGCONFIG="${BUILDDIR}/../../bitbake/contrib/autobuilderlog.json"`. Note the relative path starting from the build directory to outside of it. This path is not changed by *oe-selftest* anymore.

Environment variables containing relative paths from tested build directory to outside of the original build directory may need to be updated as they won't be changed by *oe-selftest*.

- Several sanity checks from the *insane* class, such as `buildpaths`, have been promoted to errors instead of warnings.
- The `license-incompatible` *ERROR\_QA* sanity check was renamed to `license-exception`.

## 17.6.2 Release notes for 5.1 (styhead)

### New Features / Enhancements in 5.1

- Linux kernel 6.10, gcc 14.2, glibc 2.40, LLVM 18.1.18, and over 300 other recipe upgrades.
- New variables:
  - `CVE_CHECK_MANIFEST_JSON_SUFFIX`: suffix for the CVE JSON manifest file.
  - *PRSERV\_UPSTREAM*: Upstream PR service (`host:port`) for the local PR server to connect to.
  - *RECIPE\_UPGRADE\_EXTRA\_TASKS*: space-delimited list of tasks to run after the new sources have been unpacked in the `scripts/lib/devtool/upgrade.py` `upgrade()` method.

- `UNPACKDIR`: allow change of the `do_unpack` task directory.
- Kernel-related changes:
- The default kernel is the current stable (6.10), and there is also support for the latest long-term release (6.6).
- New core recipes:
  - `fmt`: an open-source formatting library for C++ (imported from meta-oe).
  - `xcb-util-errors`: gives human readable names to error codes and event codes
- QEMU / `runqemu` changes:
  - `runqemu`: `QB_DRIVE_TYPE` now supports sd card (`/dev/mmcblk`)
  - Trigger `write_qemuboot_conf` task on changes of kernel image realpath (`KERNEL_IMAGE_NAME`).
- Go changes:
  - New Go module fetcher (`gomod://`) for downloading module dependencies to the module cache from a module proxy.
  - New Go module fetcher (`gomodgit://`) for downloading module dependencies to the module cache directly from a git repository.
  - The old 1.4 Go bootstrap written in C has been dropped. The default Go bootstrap provider is now `go-binary-native` only.
- Rust changes:
  - Cargo dependencies specified as git repositories now also have their git submodules checked out.
  - Rust is now built with its default set of tools instead of `just rust-demangler`.
- wic Image Creator changes:
  - Add the `truncate` utility in `HOSTTOOLS`, needed by some wic commands.
  - The `get_boot_files` function is no longer part of the `bootimg-partition` plugin and is part of the common `bootfiles.py` library.
- SDK-related changes:
  - Included `nativesdk-python3-pip` in `buildtools` by default.
  - `nativesdk` now have `do_package_qa` run when calling `do_populate_sdk`.
  - A new 7zip archive type can be used to create the SDK by setting `SDK_ARCHIVE_TYPE` to `7zip`.
  - The `toolchain-scripts` class now exports the target endianness and wordsize in environment variables `OECORE_TARGET_BITS` and `OECORE_TARGET_ENDIAN`.
- Testing-related changes:
  - `oeqa/selftest`: Only rewrite envvars paths that absolutely point to `BUILDDIR`.
  - `oeqa/manual`: remove obsolete CROPS and Eclipse manually testing scripts
  - Enable `ptests` for `python3-cffi`, `python3-idna`, `python3-libarchive-c`, `python3-mako`, `python3-packaging`, `python3-uritools` and `python3-rpds-py`.

- Running tests on target with *testimage* can now be done over a serial connection.
- Artifact collection when using the *testimage* class is now optional and allowed by making *TESTIMAGE\_FAILED\_QA\_ARTIFACTS* empty.
- Artifacts from *oeqa* post-actions are now retrieved as whole archives instead of individual copies. The archive is left uncompressed on the host.
- A test for the *minidebuginfo* feature of *DISTRO\_FEATURES* is now part of the test suite.
- A test for building a kernel module was added to the SDK test suite.
- *oeqa/selftest*: run test serially if neither the *testtools* or *subunit* Python modules have been found.
- Artifact collection and test result collection are now separated and artifact collection can be controlled with the *OEQA\_ARTEFACT\_DIR* variable.
- Utility script changes:
  - New *cve-json-to-text* script that converts the *cve-check* result from the JSON format to the TEXT format as *cve-check* removed text format.
  - New *makefile-getvar* script to extract value from a Makefile.
  - New *pull-spdx-licenses* script to pull SPDX license data, update license list JSON data and update license directory.
  - Several improvements in *oe-build-perf-report* report.
  - *oe-debuginfod*: add parameter "-d" to store debuginfod files in project sub-directory.
  - *resulttool*: support test report generation in JUnit XML format.
  - Remove *install-buildtools* "test installation" step harmless error messages.
  - *bitbake-layers*: add a new subcommand *show-machines* to list the machines available in the currently configured layers.
- BitBake changes:
  - Fetcher for Rust crates: added a check for latest upstream version.
  - *syncrpc* now requires a minimum version of the *websockets* module depend on Python version.
  - Improve *bitbake-hashclient* stress statistics reporting.
  - *bitbake-hashserv* added *reuseport* parameter to enable *SO\_REUSEPORT*, allowing multiple servers to bind to the same port for load balancing
  - Improve cloning speed with *BB\_GIT\_SHALLOW* and *BB\_GENERATE\_MIRROR\_TARBALLS*.
  - *BitBake* UI now includes log paths for failed task.
  - *fetcher2*: support for *wget* and *wget2*.
  - *fetcher2*: support npm package name with '@' character.
  - *fetcher2*: remote name for *git://* is now *origin* by default.
  - *Codeparser* now supports shell substitution in quotes, for example:

```
var1="$(cmd1 ...)"
```

- Function code of pylib functions are now taken into account when computing taskhashes.
- Fix `_test_devtool_add_git_url` test
- Hashserv: add a batch stream API that reduces the round trip latency on the server.
- The `prserv` class now uses a shared sqlite3 database to allow multiple processes to access the database.
- The Python codeparser now skips the checksumming of external Python modules imported with `from module import something`.
- Enable batching of `unihash` queries to reduce the effect of latency when making multiple queries to the server.
- Parser: improve cache invalidation reliability by using the `mtime`'s nanoseconds, inode number and size of files.
- When using the syntax `addtask do_XXX before YYY after ZZZ`, `bitbake` now ensures that `YYY` and `ZZZ` are prefixed with `do_`, to avoid unexpected failures.
- devtool changes:
  - Fix `_test_devtool_add_git_url` test
  - `update-recipe, finish`: fix error when calling on another layer and having a localfile.
  - `devtool check-upgrade-status` now groups recipes when they need to be upgraded together.
- Packaging changes:
  - When processing `pkgconfig`'s `pc` files, also process "Requires.private" in addition to "Requires". This fixes a broken dependency list for IPKs and avoids installing unnecessary recommended additional packages (and save disk usage).
  - Package management: make the extraction of IPK packages not depend on `zst` compression, as it can be changed with `OPKGBUILDCMD`.
  - Remove support for `DIRFILES` of `package_rpm` as it is rpm-specific and untested.
  - Bump `abi_version` and package versions after recent `pkgconfig` changes.
- Security changes:
  - The `busybox` default configuration now disables internal TLS code to use the `openssl` backend instead, for a more secure initial set of settings.
  - Limit ssh host keys pre-generation to `qemu` machines by default, for security purposes.
- LLVM related changes:
  - Enable `libllvm` in `PACKAGECONFIG` for native builds.
  - Fetch release tarballs instead of git checkouts to reduce disk usage.
- `cve-check` changes:
  - The class `cve-check` now uses a local copy of the NVD database during builds.

- New statuses can be reported by `cve-check`:
  - \* `fix-file-included`: when a fix file has been included (set automatically)
  - \* `version-not-in-range`: version number NOT in the vulnerable range (set automatically)
  - \* `version-in-range`: version number IS in the vulnerable range (set automatically)
  - \* `unknown`: impossible to conclude if the vulnerability is present or not
- The TEXT output format was removed to favor the JSON format which offers more features.
- Allow overriding the default "policies" from `meta/conf/cve-check-map.conf` by including it before distro include files in `meta/conf/bitbake.conf`.
- SPDX-related changes:
  - Update the SPDX license set too version 3.24.0, and produce SPDX output in version 3.0 by default, instead of 2.2.
  - New `create-spdx-3.0` class to generate SPDX 3.0 output (used by generic class `create-spdx`). New `create-spdx-image-3.0` class that is used when generating images and `create-spdx-sdk-3.0` for SDK based recipes.
  - New `nospdx` class that allows recipes to opt out of generating SPDX.
  - Specify the SPDX image purposes for `tar`, `cpio` and `wic` images.
  - The `create-spdx` class now reports for `multilib*` classes.
- Miscellaneous changes:
  - Fix reproducibility for `spirv-tools`
  - Allow selection of host key types used by `openssh`.
  - New `glibc` task `do_symlist` to list exported symbols.
  - `initramfs-framework` support for force reboot in the case of fatal error.
  - The `insane` class now checks for `patch-status` and `pep517-backend` by default.
  - New `yocto-space-optimize` include file to allow turning off debug compiler options for a small set of recipes to reduce build on disk footprint and package/ssstate sizes.
  - Image creation tasks inheriting from the `image` class now produce a `manifest.json` file listing the images created. The output manifest path is defined by the `IMAGE_OUTPUT_MANIFEST` variable.
  - New `vex` class generates the minimum information that is necessary for VEX generation by an external CVE checking tool.
  - New `retain` class creates a tarball of the work directory for a recipe when one of its tasks fails, or any other nominated directories.
  - New `localpkgfeed` class in `meta-selftest` to create a subset of the package feed that just contain the packages depended on by this recipe.
  - New `PACKAGECONFIG` options for individual recipes:
    - \* `appstream`: `qt6`

- \* `cronie`: `inotify`
  - \* `gststreamer1.0-plugins-bad`: `gtk3`
  - \* `libsdl2`: `libsamplerate`
  - \* `mesa`: `tegra`
  - \* `openssh`: `hostkey-rsa hostkey-ecdsa hostkey-ed25519`
  - \* `pciutils`: `kmod zlib`
  - \* `piglit`: `wayland`
  - \* `pulseaudio`: `oss-output`
  - \* `python3`: `staticlibpython`
  - \* `python3-jsonschema`: `format-nongpl` (previously "nongpl")
  - \* `systemd`: `bpf-framework`
  - \* `util-linux`: `libmount-mountfd-support`
- Stop referring to `WORKDIR` for `S` and `B` and trigger *insane* errors when `S` or `B` are equal to `WORKDIR`.
  - `picolibc` can now be used with `TCLIBC` to build with `picolibc` as the C library.
  - `openssh` now uses `sd_notify` patch from upstream instead of custom one, which does not depend on `libsystemd` and is standalone.
  - `cmake` now uses the `${COREBASE}/scripts/git` wrapper instead of the host's, which is required during *do\_install* to call `git` while disabling `fakeroot`, and avoid "dubious ownership" `git` errors.
  - Default compiler option changes:
    - \* `BUILD_CFLAGS` now includes the `-pipe` option by default.
    - \* Remove the `eliminate-unused-debug-types` option from the default compiler options since it is now included by default.
  - `uninative` updated to 4.6 for `glibc 2.40`
  - Mark `recipe meta-ide-support` as machine specific with `PACKAGE_ARCH`.
  - `sstate`: Drop `intercept functions` support which was only used by now removed `siteconfig` class.
  - `sstate`: Drop support for `SSTATEPOSTINSTFUNC` variable now that `postfunc` is available.
  - `openssl`: strip the test suite after building, reducing the build tree of 50% after installation.
  - `u-boot`: Refactor some of the *do\_configure* tasks into new functions, making it easier to modify using a `bbappend`.
  - The `musl` recipe now shows an error if used with *multilib*\* enabled (`musl` does not support `multilib`).
  - The `git` recipe is now configured with default configuration pointing to `/etc/gitconfig` for *native* recipes.
  - The `apt-native` recipe, used to compile `dpkg` and handle `deb` packages, was modified to avoid files being overridden by other packages when they share common files. Instead, prompt an error.

- The `do_savedefconfig` was moved from the u-boot and kernel recipes to the `cml1` class, so that more kbuild-based recipes can use it.
- The `sanity` class now checks if user namespaces are enabled on the host as they are required for network isolation.
- The recipe `os-release` is now part of `SIGGEN_EXCLUDERECIPES_ABISAFE` and does not trigger a rebuild on a change for dependent tasks.
- In `kernel-fitimage`, the existence of `EXTERNAL_KERNEL_DEVICETREE` is checked more thoroughly to avoid false positives.
- `rootfs`: ensure `run-postinsts` is not uninstalled when the `read-only-rootfs-delayed-postinsts` and `read-only-rootfs IMAGE_FEATURES` are enabled.
- Gcc can now use `libc++` as its runtime.
- The variable `CMDLINE_CONSOLE` was removed from the `kernel` class, as it wasn't used anywhere.
- `python3`: `make -core` depend on `-compression` as it needs to import the `zipfile` module.
- The classes `native` and `nativesdk` do not override the `*FLAGS` variables anymore, allowing users to use the `+=` syntax in recipes.
- The `multilib_script` class (part of `multilib*`) now expands the `MULTILIB_SCRIPTS` variable before splitting the scripts, fixing some issues seen when `PACKAGECONFIG` would conditionally modify it.

### Known Issues in 5.1

- `oeqa/runtime`: the `beaglebone-yocto` target fails the `parselogs` runtime test due to unexpected kernel error messages in the log (see [bug 15624](#) on Bugzilla).

### Recipe License changes in 5.1

The following corrections have been made to the `LICENSE` values set by recipes:

- `ccache`: `GPL-3.0-or-later` to `GPL-3.0-or-later & MIT & BSL-1.0 & ISC` after adding third-party licenses.
- `dejagnu`: `update` to `GPL-3.0-only`.
- `gcr`: `update` to `LGPL-2.0-only`.
- `glibc`: `update` to `GPL-2.0-only & LGPL-2.1-or-later`.
- `gpgme`: `update` for different packages.
- `iw`: `update` to `ISC`.
- `json-glib`: `LGPL-2.1-only` to `LGPL-2.1-or-later` after update to 1.10.0.
- `libgcrypt`: `GPL-2.0-or-later & LGPL-2.1-or-later` to `GPL-2.0-or-later & LGPL-2.1-or-later & BSD-3-Clause`. Add `BSD-3-Clause` for `poly1305-amd64-avx512.S`.
- `linux-firmware`: set package `LICENSE` for following firmware packages: - `cc33xx` - `ath10k-wcn3990` - `qcom-adreno-g750` - `qcom-x1e80100-adreno` - `wfx` - `qcom-vpu` - `qcom-sm8550-audio-tplg` - `qcom-sm8650-audio-tplg` - `linaro-license` - `mali-csffw-arch108`



- lz4: BSD-2-Clause | GPL-2.0-only to BSD-2-Clause | GPL-2.0-or-later after update to 1.10.0.
- ppp: add license RSA-MD .
- python3-docutils: PSF-2.0 & BSD-2-Clause & GPL-3.0-only to CC0-1.0 & ZPL-2.1 & BSD-2-Clause & GPL-3.0-only. Add CC0 after update to 0.21.2.
- tiff: update to libtiff.
- unzip: update to Info-ZIP.
- util-linux: Add GPL-2.0-only after update to 2.40.1 (GPL-2.0 changed to GPL-2.0-only in README.licensing).
- xz: PD removed and 0BSD added after update to 5.6.2.
- xz: add PD for xz, xz-dev and xz-doc package.
- zip: update to Info-ZIP.

### Security Fixes in 5.1

- apr: CVE-2023-49582
- busybox: CVE-2021-42380, CVE-2023-42363, CVE-2023-42364, CVE-2023-42365, CVE-2023-42366
- cups: CVE-2024-35235
- curl: CVE-2024-6197, CVE-2024-6874, CVE-2024-7264
- expat: CVE-2024-45490, CVE-2024-45491, CVE-2024-45492.
- gcc: CVE-2023-4039
- gdk-pixbuf: CVE-2022-48622
- ghostscript: CVE-2024-33869, CVE-2023-52722, CVE-2024-33870, CVE-2024-33871, CVE-2024-29510
- git: CVE-2024-32002, CVE-2024-32004, CVE-2024-32020, CVE-2024-32021, CVE-2024-32465
- glibc: CVE-2024-2961, CVE-2024-33599, CVE-2024-33600, CVE-2024-33601, CVE-2024-33602
- go: CVE-2024-24790
- gtk+3: CVE-2024-6655
- linux-yocto/6.10: CVE-2020-16119
- linux-yocto/6.6: CVE-2020-16119
- llvm: CVE-2024-0151
- ncurses: CVE-2023-50495, CVE-2023-45918
- openssh: CVE-2024-6387
- openssl: CVE-2024-4603, CVE-2024-4741
- ovmf: CVE-2023-45236, CVE-2023-45237, CVE-2024-25742
- python3: CVE-2024-7592, CVE-2024-8088, CVE-2024-6232

- ruby: CVE-2024-27282, CVE-2024-27281, CVE-2024-27280
- tiff: CVE-2024-7006
- vim: CVE-2024-41957, CVE-2024-41965, CVE-2024-43374, CVE-2024-43790, CVE-2024-43802
- wget: CVE-2024-38428
- wpa-supPLICant: CVE-2024-5290, CVE-2023-52160
- xserver-xorg: CVE-2024-31080, CVE-2024-31081, CVE-2024-31082, CVE-2024-31083

## Recipe Upgrades in 5.1

- acpica 20240322 -> 20240827
- adwaita-icon-theme 45.0 -> 46.2
- alsa-lib 1.2.11 -> 1.2.12
- alsa-plugins 1.2.7.1 -> 1.2.12
- alsa-ucm-conf 1.2.11 -> 1.2.12
- alsa-utils 1.2.11 -> 1.2.12
- asciidoc 10.2.0 -> 10.2.1
- at-spi2-core 2.50.1 -> 2.52.0
- attr 2.5.1 -> 2.5.2
- automake 1.16.5 -> 1.17
- base-passwd 3.6.3 -> 3.6.4
- bash 5.2.21 -> 5.2.32
- bash-completion 2.12.0 -> 2.14.0
- bind 9.18.28 -> 9.20.1
- binutils 2.42 -> 2.43.1
- binutils-cross 2.42 -> 2.43.1
- binutils-cross-canadian 2.42 -> 2.43.1
- binutils-crosssdk 2.42 -> 2.43.1
- bluez5 5.72 -> 5.78
- boost 1.84.0 -> 1.86.0
- boost-build-native 1.84.0 -> 1.86.0
- btrfs-tools 6.7.1 -> 6.10.1
- build-appliance-image 15.0.0 (bf88a67b4523...) -> 15.0.0 (7cc8bf7af794...)
- ca-certificates 20211016 -> 20240203
- cairo 1.18.0 -> 1.18.2

- cargo 1.75.0 -> 1.79.0
- cargo-c-native 0.9.30+cargo-0.77.0 -> 0.10.3+cargo-0.81.0
- ccache 4.9.1 -> 4.10.2
- cmake 3.28.3 -> 3.30.2
- cmake-native 3.28.3 -> 3.30.2
- connman 1.42 -> 1.43
- coreutils 9.4 -> 9.5
- cracklib 2.9.11 -> 2.10.2
- createrepo-c 1.0.4 -> 1.1.4
- cross-localedef-native 2.39+git -> 2.40+git
- cryptodev-linux 1.13+gitX -> 1.14
- cryptodev-module 1.13+gitX -> 1.14
- cryptodev-tests 1.13+gitX -> 1.14
- curl 8.7.1 -> 8.9.1
- debianutils 5.16 -> 5.20
- dhcpcd 10.0.6 -> 10.0.10
- diffoscope 259 -> 277
- dmidecode 3.5 -> 3.6
- dnf 4.19.0 -> 4.21.1
- dpkg 1.22.0 -> 1.22.11
- dropbear 2022.83 -> 2024.85
- e2fsprogs 1.47.0 -> 1.47.1
- ell 0.64 -> 0.68
- enchant2 2.6.7 -> 2.8.2
- encodings 1.0.7 -> 1.1.0
- epiphany 46.0 -> 46.3
- erofs-utils 1.7.1 -> 1.8.1
- ethtool 6.7 -> 6.10
- ffmpeg 6.1.1 -> 7.0.2
- findutils 4.9.0 -> 4.10.0
- freetype 2.13.2 -> 2.13.3
- fribibidi 1.0.14 -> 1.0.15

- gcc 13.3.0 -> 14.2.0
- gcc-cross 13.3.0 -> 14.2.0
- gcc-cross-canadian 13.3.0 -> 14.2.0
- gcc-crosssdk 13.3.0 -> 14.2.0
- gcc-runtime 13.3.0 -> 14.2.0
- gcc-sanitizers 13.3.0 -> 14.2.0
- gcc-source 13.3.0 -> 14.2.0
- gcr 4.2.1 -> 4.3.0
- gdb 14.2 -> 15.1
- gdb-cross 14.2 -> 15.1
- gdb-cross-canadian 14.2 -> 15.1
- gdbm 1.23 -> 1.24
- gi-docgen 2023.3 -> 2024.1
- git 2.44.1 -> 2.46.0
- glib-2.0 2.78.6 -> 2.82.1
- glib-networking 2.78.1 -> 2.80.0
- glibc 2.39+git -> 2.40+git
- glibc-locale 2.39+git -> 2.40+git
- glibc-mtrace 2.39+git -> 2.40+git
- glibc-scripts 2.39+git -> 2.40+git
- glibc-testsuite 2.39+git -> 2.40+git
- glibc-y2038-tests 2.39+git -> 2.40+git
- glslang 1.3.275.0 -> 1.3.290.0
- gnu-config 20240101+git -> 20240823+git
- gnu-efi 3.0.17 -> 3.0.18
- gnupg 2.4.4 -> 2.5.0
- gnutls 3.8.4 -> 3.8.6
- go-helloworld 0.1 (d9923f6970e9...) -> 0.1 (39e772fc2670...)
- gobject-introspection 1.78.1 -> 1.80.1
- gptfdisk 1.0.9 -> 1.0.10
- gsettings-desktop-schemas 46.0 -> 47.1
- gst-devtools 1.22.12 -> 1.24.6

- gstreamer1.0 1.22.12 -> 1.24.6
- gstreamer1.0-libav 1.22.12 -> 1.24.6
- gstreamer1.0-plugins-bad 1.22.12 -> 1.24.6
- gstreamer1.0-plugins-base 1.22.12 -> 1.24.6
- gstreamer1.0-plugins-good 1.22.12 -> 1.24.6
- gstreamer1.0-plugins-ugly 1.22.12 -> 1.24.6
- gstreamer1.0-python 1.22.12 -> 1.24.6
- gstreamer1.0-rtsp-server 1.22.12 -> 1.24.6
- gstreamer1.0-vaapi 1.22.12 -> 1.24.6
- gtk+3 3.24.41 -> 3.24.43
- gtk-doc 1.33.2 -> 1.34.0
- gtk4 4.14.1 -> 4.16.0
- harfbuzz 8.3.0 -> 9.0.0
- hicolor-icon-theme 0.17 -> 0.18
- hwlatdetect 2.6 -> 2.7
- icu 74-2 -> 75-1
- ifupdown 0.8.41 -> 0.8.43
- iproute2 6.7.0 -> 6.10.0
- iputils 20240117 -> 20240905
- iw 6.7 -> 6.9
- json-glib 1.8.0 -> 1.10.0
- kea 2.4.1 -> 2.6.1
- kexec-tools 2.0.28 -> 2.0.29
- kmod 31 -> 33
- kmscube 0.0.1+git (6ab022fdcfce...) -> 0.0.1+git (467e86c5cbeb...)
- less 643 -> 661
- libadwaita 1.5.2 -> 1.6.0
- libassuan 2.5.6 -> 3.0.1
- libbsd 0.12.1 -> 0.12.2
- libcap 2.69 -> 2.70
- libcomps 0.1.20 -> 0.1.21
- libdnf 0.73.2 -> 0.73.3

- libdrm 2.4.120 -> 2.4.123
- libedit 20230828-3.1 -> 20240808-3.1
- libevdev 1.13.1 -> 1.13.2
- libfontenc 1.1.7 -> 1.1.8
- libgcc 13.3.0 -> 14.2.0
- libgcc-initial 13.3.0 -> 14.2.0
- libgcrypt 1.10.3 -> 1.11.0
- libgfortran 13.3.0 -> 14.2.0
- libgit2 1.7.2 -> 1.8.1
- libgpg-error 1.48 -> 1.50
- libical 3.0.17 -> 3.0.18
- libinput 1.25.0 -> 1.26.1
- libjitterentropy 3.4.1 -> 3.5.0
- libksba 1.6.6 -> 1.6.7
- libnl 3.9.0 -> 3.10.0
- libpam 1.5.3 -> 1.6.1
- libpcap 1.10.4 -> 1.10.5
- libpciaccess 0.18 -> 0.18.1
- libpcre2 10.43 -> 10.44
- libpng 1.6.42 -> 1.6.43
- libportal 0.7.1 -> 0.8.1
- libproxy 0.5.4 -> 0.5.8
- librepo 1.17.0 -> 1.18.1
- librsvg 2.57.1 -> 2.58.2
- libSDL2 2.30.1 -> 2.30.7
- libslirp 4.7.0 -> 4.8.0
- libsolve 0.7.28 -> 0.7.30
- libsoup 3.4.4 -> 3.6.0
- libstd-rs 1.75.0 -> 1.79.0
- libtirpc 1.3.4 -> 1.3.5
- libtool 2.4.7 -> 2.5.2
- libtool-cross 2.4.7 -> 2.5.2

- libtool-native 2.4.7 -> 2.5.2
- libtraceevent 1.7.3 -> 1.8.3
- liburcu 0.14.0 -> 0.14.1
- liburi-perl 5.27 -> 5.28
- libva 2.20.0 -> 2.22.0
- libva-initial 2.20.0 -> 2.22.0
- libva-utils 2.20.1 -> 2.22.0
- libwebp 1.3.2 -> 1.4.0
- libwpe 1.14.2 -> 1.16.0
- libx11 1.8.9 -> 1.8.10
- libxcb 1.16 -> 1.17.0
- libxdmcp 1.1.4 -> 1.1.5
- libxfont2 2.0.6 -> 2.0.7
- libxkbcommon 1.6.0 -> 1.7.0
- libxml2 2.12.8 -> 2.13.3
- libxmlb 0.3.15 -> 0.3.19
- libxmu 1.1.4 -> 1.2.1
- libxslt 1.1.39 -> 1.1.42
- libxtst 1.2.4 -> 1.2.5
- lighttpd 1.4.74 -> 1.4.76
- linux-firmware 20240312 -> 20240909
- linux-libc-headers 6.6 -> 6.10
- linux-yocto 6.6.35+git -> 6.6.50+git, 6.10.8+git
- linux-yocto-dev 6.9+git -> 6.11+git
- linux-yocto-rt 6.6.35+git -> 6.6.50+git, 6.10.8+git
- linux-yocto-tiny 6.6.35+git -> 6.6.50+git, 6.10.8+git
- llvm 18.1.6 -> 18.1.8
- logrotate 3.21.0 -> 3.22.0
- ltp 20240129 -> 20240524
- lttng-modules 2.13.12 -> 2.13.14
- lttng-tools 2.13.13 -> 2.13.14
- lua 5.4.6 -> 5.4.7

- `lz4` 1.9.4 -> 1.10.0
- `lzip` 1.24 -> 1.24.1
- `man-db` 2.12.0 -> 2.12.1
- `man-pages` 6.06 -> 6.9.1
- `mc` 4.8.31 -> 4.8.32
- `mdadm` 4.2 -> 4.3
- `meson` 1.3.1 -> 1.5.1
- `mkfontscale` 1.2.2 -> 1.2.3
- `mmc-utils` 0.1+git (b5ca140312d2...) -> 0.1+git (123fd8b2ac39...)
- `mpg123` 1.32.6 -> 1.32.7
- `msmtp` 1.8.25 -> 1.8.26
- `mtdev` 2.1.6 -> 2.2.0
- `mtdev` 1.1.6 -> 1.1.7
- `mttools` 4.0.43 -> 4.0.44
- `musl` 1.2.4+git -> 1.2.5+git
- `nativesdk-libtool` 2.4.7 -> 2.5.2
- `ncurses` 6.4 -> 6.5
- `nettle` 3.9.1 -> 3.10
- `nfs-utils` 2.6.4 -> 2.7.1
- `nghttp2` 1.61.0 -> 1.63.0
- `ninja` 1.11.1 -> 1.12.1
- `npth` 1.6 -> 1.7
- `ofono` 2.4 -> 2.10
- `opensbi` 1.4 -> 1.5.1
- `openssh` 9.6p1 -> 9.8p1
- `openssl` 3.2.3 -> 3.3.1
- `opkg` 0.6.3 -> 0.7.0
- `opkg-utils` 0.6.3 -> 0.7.0
- `ovmf` edk2-stable202402 -> edk2-stable202408
- `p11-kit` 0.25.3 -> 0.25.5
- `pango` 1.52.1 -> 1.54.0
- `pciutils` 3.11.1 -> 3.13.0



- perl 5.38.2 -> 5.40.0
- perlcross 1.5.2 -> 1.6
- piglit 1.0+gitr (22eaf6a91cfd...) -> 1.0+gitr (c11c9374c144...)
- pinentry 1.2.1 -> 1.3.1
- pkgconf 2.1.1 -> 2.3.0
- psmisc 23.6 -> 23.7
- ptest-runner 2.4.4+git -> 2.4.5+git
- puzzles 0.0+git (80aac3104096...) -> 0.0+git (1c1899ee1c4e...)
- python3-alabaster 0.7.16 -> 1.0.0
- python3-attrs 23.2.0 -> 24.2.0
- python3-babel 2.14.0 -> 2.16.0
- python3-bcrypt 4.1.2 -> 4.2.0
- python3-beartype 0.17.2 -> 0.18.5
- python3-build 1.1.1 -> 1.2.1
- python3-certifi 2024.2.2 -> 2024.8.30
- python3-cffi 1.16.0 -> 1.17.0
- python3-cryptography 42.0.5 -> 42.0.8
- python3-cryptography-vectors 42.0.5 -> 42.0.8
- python3-cython 3.0.8 -> 3.0.11
- python3-dbusmock 0.31.1 -> 0.32.1
- python3-docutils 0.20.1 -> 0.21.2
- python3-dtschema 2024.2 -> 2024.5
- python3-git 3.1.42 -> 3.1.43
- python3-hatchling 1.21.1 -> 1.25.0
- python3-hypothesis 6.98.15 -> 6.111.2
- python3-idna 3.7 -> 3.8
- python3-jsonpointer 2.4 -> 3.0.0
- python3-jsonschema 4.21.1 -> 4.23.0
- python3-libarchive-c 5.0 -> 5.1
- python3-license-expression 30.2.0 -> 30.3.1
- python3-lxml 5.0.0 -> 5.3.0
- python3-mako 1.3.2 -> 1.3.5

- python3-markdown 3.5.2 -> 3.6
- python3-maturin 1.4.0 -> 1.7.1
- python3-meson-python 0.15.0 -> 0.16.0
- python3-more-itertools 10.2.0 -> 10.4.0
- python3-packaging 23.2 -> 24.1
- python3-pbr 6.0.0 -> 6.1.0
- python3-pip 24.0 -> 24.2
- python3-pluggy 1.4.0 -> 1.5.0
- python3-psutil 5.9.8 -> 6.0.0
- python3-pyasn1 0.5.1 -> 0.6.0
- python3-pycairo 1.26.0 -> 1.26.1
- python3-pycparser 2.21 -> 2.22
- python3-pyelftools 0.30 -> 0.31
- python3-pygments 2.17.2 -> 2.18.0
- python3-pyobject 3.46.0 -> 3.48.2
- python3-pyopenssl 24.0.0 -> 24.2.1
- python3-pyparsing 3.1.1 -> 3.1.4
- python3-pyproject-metadata 0.7.1 -> 0.8.0
- python3-pytest 8.0.2 -> 8.3.2
- python3-pytest-subtests 0.11.0 -> 0.13.1
- python3-pyyaml 6.0.1 -> 6.0.2
- python3-referencing 0.33.0 -> 0.35.1
- python3-requests 2.31.0 -> 2.32.3
- python3-rpds-py 0.18.0 -> 0.20.0
- python3-scons 4.6.0 -> 4.8.0
- python3-setuptools 69.1.1 -> 72.1.0
- python3-setuptools-rust 1.9.0 -> 1.10.1
- python3-setuptools-scm 8.0.4 -> 8.1.0
- python3-sphinx 7.2.6 -> 8.0.2
- python3-sphinxcontrib-applehelp 1.0.8 -> 2.0.0
- python3-sphinxcontrib-devhelp 1.0.6 -> 2.0.0
- python3-sphinxcontrib-htmlhelp 2.0.5 -> 2.1.0

- python3-sphinxcontrib-qthelp 1.0.7 -> 2.0.0
- python3-sphinxcontrib-serializinghtml 1.1.10 -> 2.0.0
- python3-testtools 2.7.1 -> 2.7.2
- python3-trove-classifiers 2024.2.23 -> 2024.7.2
- python3-typing-extensions 4.10.0 -> 4.12.2
- python3-uritools 4.0.2 -> 4.0.3
- python3-urllib3 2.2.1 -> 2.2.2
- python3-webcolors 1.13 -> 24.8.0
- python3-websockets 12.0 -> 13.0.1
- python3-wheel 0.42.0 -> 0.44.0
- python3-zipp 3.17.0 -> 3.20.1
- qemu 8.2.3 -> 9.0.2
- qemu-native 8.2.3 -> 9.0.2
- qemu-system-native 8.2.3 -> 9.0.2
- quilt 0.67 -> 0.68
- quilt-native 0.67 -> 0.68
- readline 8.2 -> 8.2.13
- repo 2.42 -> 2.46
- rng-tools 6.16 -> 6.17
- rpcbind 1.2.6 -> 1.2.7
- rsync 3.2.7 -> 3.3.0
- rt-tests 2.6 -> 2.7
- ruby 3.2.2 -> 3.3.4
- rust 1.75.0 -> 1.79.0
- rust-cross-canadian 1.75.0 -> 1.79.0
- rust-llvm 1.75.0 -> 1.79.0
- shaderc 2023.8 -> 2024.1
- shadow 4.14.2 -> 4.16.0
- spirv-headers 1.3.275.0 -> 1.3.290.0
- spirv-tools 1.3.275.0 -> 1.3.290.0
- sqlite3 3.45.1 -> 3.46.1
- strace 6.7 -> 6.10

- stress-ng 0.17.05 -> 0.18.02
- sysklogd 2.5.2 -> 2.6.1
- sysstat 12.7.5 -> 12.7.6
- systemd 255.4 -> 256.5
- systemd-boot 255.4 -> 256.5
- systemd-boot-native 255.4 -> 256.5
- systemtap 5.0 -> 5.1
- systemtap-native 5.0 -> 5.1
- taglib 2.0.1 -> 2.0.2
- tcl 8.6.13 -> 8.6.14
- texinfo 7.0.3 -> 7.1
- ttyrun 2.31.0 -> 2.34.0
- u-boot 2024.01 -> 2024.07
- u-boot-tools 2024.01 -> 2024.07
- util-linux 2.39.3 -> 2.40.2
- util-linux-libuuid 2.39.3 -> 2.40.2
- util-macros 1.20.0 -> 1.20.1
- vala 0.56.15 -> 0.56.17
- valgrind 3.22.0 -> 3.23.0
- vte 0.74.2 -> 0.76.3
- vulkan-headers 1.3.275.0 -> 1.3.290.0
- vulkan-loader 1.3.275.0 -> 1.3.290.0
- vulkan-samples git (2307c3eb5608...) -> git (fdce530c0295...)
- vulkan-tools 1.3.275.0 -> 1.3.290.0
- vulkan-utility-libraries 1.3.275.0 -> 1.3.290.0
- vulkan-validation-layers 1.3.275.0 -> 1.3.290.0
- vulkan-volk 1.3.275.0 -> 1.3.290.0
- waffle 1.7.2 -> 1.8.1
- wayland 1.22.0 -> 1.23.1
- wayland-protocols 1.33 -> 1.37
- webkitgtk 2.44.1 -> 2.44.3
- weston 13.0.1 -> 13.0.3

- wget 1.21.4 -> 1.24.5
- wpa-supPLICANT 2.10 -> 2.11
- x264 r3039+git (baee400fa9ce...) -> r3039+git (31e19f92f00c...)
- xauth 1.1.2 -> 1.1.3
- xcb-PROTO 1.16.0 -> 1.17.0
- xev 1.2.5 -> 1.2.6
- xkeyboard-config 2.41 -> 2.42
- xmlto 0.0.28+0.0.29+git -> 0.0.29
- xorgproto 2023.2 -> 2024.1
- xwayland 23.2.5 -> 24.1.2
- xz 5.4.6 -> 5.6.2
- zstd 1.5.5 -> 1.5.6

## Contributors to 5.1

Thanks to the following people who contributed to this release:

- Adithya Balakumar
- Adriaan Schmidt
- Adrian Freihofer
- Alban Bedel
- Alejandro Hernandez Samaniego
- Aleksandar Nikolic
- Alessandro Pecugi
- Alexander Kanavin
- Alexander Sverdlin
- Alexandre Belloni
- Alexandre Truong
- Alexis Lothoré
- Andrew Fernandes
- Andrew Oppelt
- Andrey Zhizhikin
- Anton Almqvist
- Antonin Godard
- Anuj Mittal

- Archana Polampalli
- Bartosz Golaszewski
- Benjamin Bara
- Benjamin Szőke
- Bruce Ashfield
- Carlos Alberto Lopez Perez
- Changhyeok Bae
- Changqing Li
- Chen Qi
- Chris Laplante
- Chris Spencer
- Christian Bräuner Sørensen
- Christian Lindeberg
- Christian Taedcke
- Clara Kowalsky
- Clément Péron
- Colin McAllister
- Corentin Lévy
- Daniel Klauer
- Daniel Semkowicz
- Daniil Batalov
- Dan McGregor
- Deepesh Varatharajan
- Deepthi Hemraj
- Denys Dmytriienko
- Divya Chellam
- Dmitry Baryshkov
- Emil Kronborg
- Enguerrand de Ribaucourt
- Enrico Jörns
- Esben Haabendal
- Etienne Cordonnier

- Fabio Estevam
- Felix Nilsson
- Florian Amstutz
- Gassner, Tobias.ext
- Gauthier HADERER
- Guðni Már Gilbert
- Harish Sadineni
- Heiko Thole
- Het Patel
- Hongxu Jia
- Igor Opaniuk
- Intaek Hwang
- Iskander Amara
- Jaeyoon Jung
- Jan Vermaete
- Jasper Orschulko
- Joe Slater
- Johannes Schneider
- John Ripple
- Jonas Gorski
- Jonas Munsin
- Jonathan GUILLOT
- Jon Mason
- Jookia
- Jordan Crouse
- Jörg Sommer
- Jose Quaresma
- Joshua Watt
- Julien Stephan
- Kai Kang
- Kari Sivonen
- Khem Raj

- Kirill Yatsenko
- Konrad Weihmann
- Lee Chee Yang
- Lei Maohui
- Leon Anavi
- Leonard Göhrs
- Louis Rannou
- Marc Ferland
- Marcus Folkesson
- Marek Vasut
- Mark Hatle
- Markus Volk
- Marlon Rodriguez Garcia
- Marta Rybczynska
- Martin Hundebøll
- Martin Jansa
- Matthew Bullock
- Matthias Pritschet
- Maxin B. John
- Michael Glembotzki
- Michael Haener
- Michael Halstead
- Michael Opdenacker
- Michal Sieron
- Mikko Rapeli
- Mingli Yu
- Naveen Saini
- Niko Mauno
- Ninette Adhikari
- Noe Galea
- Ola x Nilsson
- Oleksandr Hnatiuk



- Otavio Salvador
- Patrick Wicki
- Paul Barker
- Paul Eggleton
- Paul Gerber
- Pedro Ferreira
- Peter Kjellerstedt
- Peter Marko
- Philip Lorenz
- Poonam Jadhav
- Primož Fiser
- Quentin Schulz
- Ralph Siemsen
- Rasmus Villemoes
- Ricardo Simoes
- Richard Purdie
- Robert Joslyn
- Robert Kovacsics
- Robert Yang
- Ross Burton
- Rudolf J Streif
- Ryan Eatmon
- Sabeeh Khan
- Sakib Sajal
- Samantha Jalabert
- Siddharth Doshi
- simit.ghane
- Simone Weiß
- Soumya Sambu
- Sreejith Ravi
- Stefan Mueller-Klieser
- Sundeep KOKKONDA

- Sven Schwermer
- Teresa Remmet
- Theodore A. Roth
- Thomas Perrot
- Tim Orling
- Tom Hochstein
- Trevor Gamblin
- Troels Dalsgaard Hoffmeyer
- Tronje Krabbe
- Ulrich Ölmann
- Victor Kamensky
- Vijay Anusuri
- Vincent Kriek
- Vivek Puar
- Wadim Egorov
- Wang Mingyu
- Weisser, Pascal.ext
- Willy Tu
- Xiangyu Chen
- Yang-Mark Zhang
- Yash Shinde
- Yi Zhao
- Yoann Congal
- Yogita Urade
- Yuri D'Elia
- Zahir Hussain
- Zev Weiss
- Zoltan Boszormenyi

## **Repositories / Downloads for Yocto-5.1**

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [styhead](#)

- Tag: yocto-5.1
- Git Revision: 8f01ae5c7cba251ed25c80f0141a950ebc8a5f73
- Release Artefact: poky-8f01ae5c7cba251ed25c80f0141a950ebc8a5f73
- sha: 91f5b2bc8a2be153ac2c358aa8ad71737b4f91e83d2c3ed1aac4f5f087991769
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.1/poky-8f01ae5c7cba251ed25c80f0141a950ebc8a5f73.tar.bz2> <http://mirrors.kernel.org/yocto/yocto-5.1/poky-8f01ae5c7cba251ed25c80f0141a950ebc8a5f73.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: styhead
- Tag: yocto-5.1
- Git Revision: 161c5b311f1aeb8f254dca96331b31d5b67fc92d
- Release Artefact: oecore-161c5b311f1aeb8f254dca96331b31d5b67fc92d
- sha: 7b8ea61a3b811556f40b0912ee22b3ef37bcead1d65fb7e1c35a47aff4ca718
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.1/oecore-161c5b311f1aeb8f254dca96331b31d5b67fc92d.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto-5.1/oecore-161c5b311f1aeb8f254dca96331b31d5b67fc92d.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: styhead
- Tag: yocto-5.1
- Git Revision: 4ac6cbfdce1f85294bd54bcd8b074f7ef32c378f
- Release Artefact: meta-mingw-4ac6cbfdce1f85294bd54bcd8b074f7ef32c378f
- sha: 7759361e141654cc84aad486ad36a9ddaf7ee47feebe2cc6dca3175f1922b7c4
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.1/meta-mingw-4ac6cbfdce1f85294bd54bcd8b074f7ef32c378f.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto-5.1/meta-mingw-4ac6cbfdce1f85294bd54bcd8b074f7ef32c378f.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.10
- Tag: yocto-5.1
- Git Revision: d3c84198771b7f79aa84dc73061d8ca071fe18f3
- Release Artefact: bitbake-d3c84198771b7f79aa84dc73061d8ca071fe18f3
- sha: 4b64120f26878a661d1aaf0b0bb5009a21614e2db0649c728cc9d4c16b1050b6

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.1/bitbake-d3c84198771b7f79aa84dc73061d8ca071fe18f3.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-5.1/bitbake-d3c84198771b7f79aa84dc73061d8ca071fe18f3.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: styhead
- Tag: yocto-5.1
- Git Revision: c32b55b3403dcfd76a4694ff407d4b513e14c8f4

### 17.6.3 Release notes for Yocto-5.1.1 (Styhead)

#### Security Fixes in Yocto-5.1.1

- go: Fix CVE-2024-34155, CVE-2024-34156 and CVE-2024-34158
- linux-yocto/6.6: Fix CVE-2023-52917, CVE-2024-46735, CVE-2024-46737, CVE-2024-46738, CVE-2024-46739, CVE-2024-46740, CVE-2024-46741, CVE-2024-46742, CVE-2024-46743, CVE-2024-46744, CVE-2024-46746, CVE-2024-46747, CVE-2024-46749, CVE-2024-46750, CVE-2024-46755, CVE-2024-46756, CVE-2024-46757, CVE-2024-46758, CVE-2024-46759, CVE-2024-46760, CVE-2024-46761, CVE-2024-46762, CVE-2024-46763, CVE-2024-46765, CVE-2024-46768, CVE-2024-46770, CVE-2024-46771, CVE-2024-46773, CVE-2024-46776, CVE-2024-46777, CVE-2024-46780, CVE-2024-46781, CVE-2024-46782, CVE-2024-46783, CVE-2024-46784, CVE-2024-46785, CVE-2024-46786, CVE-2024-46787, CVE-2024-46788, CVE-2024-46791, CVE-2024-46794, CVE-2024-46795, CVE-2024-46796, CVE-2024-46797, CVE-2024-46798, CVE-2024-46800, CVE-2024-46822, CVE-2024-46825, CVE-2024-46826, CVE-2024-46827, CVE-2024-46828, CVE-2024-46829, CVE-2024-46830, CVE-2024-46831, CVE-2024-46832, CVE-2024-46835, CVE-2024-46836, CVE-2024-46838, CVE-2024-46840, CVE-2024-46843, CVE-2024-46844, CVE-2024-46845, CVE-2024-46846, CVE-2024-46847, CVE-2024-46848, CVE-2024-46849, CVE-2024-46852, CVE-2024-46853, CVE-2024-46854, CVE-2024-46855, CVE-2024-46857, CVE-2024-46858, CVE-2024-46859, CVE-2024-46860, CVE-2024-46861, CVE-2024-46863, CVE-2024-46864, CVE-2024-47663, CVE-2024-47664, CVE-2024-47665, CVE-2024-47666, CVE-2024-47667, CVE-2024-47668, CVE-2024-47669, CVE-2024-47670, CVE-2024-47671, CVE-2024-47672, CVE-2024-47673, CVE-2024-47674, CVE-2024-47675, CVE-2024-47678, CVE-2024-47679, CVE-2024-47681, CVE-2024-47682, CVE-2024-47683, CVE-2024-47684, CVE-2024-47685, CVE-2024-47686, CVE-2024-47688, CVE-2024-47689, CVE-2024-47690, CVE-2024-47691, CVE-2024-47692, CVE-2024-47693, CVE-2024-47695, CVE-2024-47696, CVE-2024-47697, CVE-2024-47698, CVE-2024-47699, CVE-2024-47700, CVE-2024-47701, CVE-2024-47705, CVE-2024-47706, CVE-2024-47707, CVE-2024-47710, CVE-2024-47712, CVE-2024-47713, CVE-2024-47714, CVE-2024-47715, CVE-2024-47716, CVE-2024-47718, CVE-2024-47719, CVE-2024-47720, CVE-2024-47723, CVE-2024-47727, CVE-2024-47728, CVE-2024-47730, CVE-2024-47731, CVE-2024-47734, CVE-2024-47735, CVE-2024-47737, CVE-2024-47738, CVE-2024-47739, CVE-2024-47741, CVE-2024-47742, CVE-2024-47743, CVE-2024-47744, CVE-2024-47745, CVE-2024-47747, CVE-2024-47748, CVE-2024-47749, CVE-2024-47750, CVE-2024-47751, CVE-2024-47752, CVE-2024-47753, CVE-2024-47754, CVE-2024-47757, CVE-2024-49850, CVE-2024-49851, CVE-2024-49852, CVE-2024-49853, CVE-2024-49854, CVE-2024-



CVE-2024-47754, CVE-2024-47757, CVE-2024-49850, CVE-2024-49851, CVE-2024-49852, CVE-2024-49853, CVE-2024-49854, CVE-2024-49855, CVE-2024-49856, CVE-2024-49858, CVE-2024-49859, CVE-2024-49860, CVE-2024-49861, CVE-2024-49862, CVE-2024-49863, CVE-2024-49864, CVE-2024-49866, CVE-2024-49867, CVE-2024-49868, CVE-2024-49870, CVE-2024-49871, CVE-2024-49874 and CVE-2024-49875

- orc: Fix CVE-2024-40897 (follow-up fix)
- vim: Fix CVE-2024-45306 and CVE-2024-47814
- wpa-supPLICANT: Ignore CVE-2024-5290
- xserver-xorg: Fix CVE-2024-9632
- xwayland: Fix CVE-2024-9632

### Fixes in Yocto-5.1.1

- binutils: Add missing perl modules to *RDEPENDS* for nativesdk variant
- binutils: Fix binutils mingw packaging
- bitbake.conf: Mark VOLATILE\_LOG\_DIR & VOLATILE\_TMP\_DIR as obsolete
- bitbake: Remove custom exception backtrace formatting
- bitbake: bitbake: doc/user-manual: Update the *BB\_HASHSERVE\_UPSTREAM*
- bitbake: fetch2/git: Use quote from shlex, not pipes
- bitbake: fetch2: don't try to preserve all attributes when unpacking files
- bitbake: fetch2: use persist\_data context managers
- bitbake: fetch/wget: Increase timeout to 100s from 30s
- bitbake: git-sm: Add call\_process\_submodules() to remove duplicated code
- bitbake: git-sm: Remove downloads/tmpdir when failed
- bitbake: persist\_data: close connection in SQLTable \_\_exit\_\_
- bitbake: tests/fetch: Update GoModTest and GoModGitTest
- bitbake: tests/fetch: Use our own mirror of mobile-broadband-provider to decouple from gnome gitlab
- bitbake: tests/fetch: Use our own mirror of sysprof to decouple from gnome gitlab
- bluez: Fix mesh builds on musl
- build-appliance-image: Update to styhead head revision
- cml1.bbclass: do\_diffconfig: Don't override .config with .config.orig
- contributor-guide: Remove duplicated words
- cve-check: add field "modified" to JSON report
- cve-check: add support for cvss v4.0
- cve-check: do not skip cve status description after :

- cve-check: fix malformed cve status description with : characters
- dev-manual: add bblock documentation
- dev-manual: bblock: use warning block instead of attention
- dev-manual: document how to provide confs from layer.conf
- documentation: features: describe distribution feature pni-name
- documentation; features: remove duplicate word in distribution feature ext2
- documentation: Makefile: add SPHINXLINTDOCS to specify subset to sphinx-lint
- documentation: Makefile: add support for xelatex
- documentation: Makefile: publish pdf and epub versions too
- documentation: Makefile: remove inkscape, replace by rsvg-convert
- documentation: README: add instruction to run Vale on a subset
- documentation: Replace VOLATILE\_LOG\_DIR with *FILESYSTEM\_PERMS\_TABLES*
- documentation: Replace VOLATILE\_TMP\_DIR with *FILESYSTEM\_PERMS\_TABLES*
- documentation: add a download page for epub and pdf
- documentation: conf.py: add a bitbake\_git extlink
- documentation: conf.py: rename :cve: role to :cve\_nist:
- documentation: sphinx-static/switchers.js.in: do not refer to URL\_ROOT anymore
- documentation: styles: vocabularies: Yocto: add sstate
- e2fsprogs: removed 'sed -u' option
- efi-bootdisk.wks: Increase overhead-factor to avoid test failures
- ffmpeg: Add "libswresample libavcodec" to *CVE\_PRODUCT*
- ffmpeg: Disable asm optimizations on x86
- ffmpeg: fix packaging examples
- ffmpeg: nasm is x86 only, so only DEPEND if x86
- ffmpeg: no need for textrel *INSANE\_SKIP*
- gcc-source: Fix racing on building gcc-source-14.2.0 and lib32-gcc-source-14.2.0
- gcc: add a backport patch to fix an issue with tzdata 2024b
- git: upgrade to 2.46.1
- glib-2.0: fix glib-2.0 ptest failure when upgrading tzdata2024b
- glibc: Fix missing randomness in \_\_gen\_tmpname
- glibc: stable 2.40 branch updates
- go: upgrade to 1.22.8

- groff: fix rare build race in hdtbl
- icu: update patch Upstream-Status
- image.bbclass: Drop support for ImageQAFailed exceptions in image\_qa
- json-c: avoid ptest failure caused by valgrind
- kexec-tools: update [COMPATIBLE\\_HOST](#) because of makedumpfile
- kmscube: Upgrade to latest revision (b2f97f53e0..)
- lib/oe/package-manager: skip processing installed-pkgs with empty globs
- libevdev: upgrade to 1.13.3
- libgfortran: fix buildpath QA issue
- libpam: use libdir in conditional
- linux-yocto/6.6: update to v6.6.54
- linux-yocto/6.10: bsp/genericarm64: disable ARM64\_SME
- linux-yocto/6.10: cfg: gpio: allow to re-enable the deprecated GPIO sysfs interface
- linux-yocto/6.10: genericarm64.cfg: enable CONFIG\_DMA\_CMA
- linux-yocto/6.10: update to v6.10.14
- linux-yocto: Enable l2tp drivers when ptest feature is on
- lsb-release: fix Distro Codename shell escaping
- migration-guides/release-notes-4.0: update [BB\\_HASHSERVE\\_UPSTREAM](#) for new infrastructure
- migration-guides/release-notes-5.0: NO\_OUTPUT -> NO\_COLOR
- migration-guides/release-notes-5.1: add beaglebone-yocto parselogs test oeqa failure
- migration-guides/release-notes-5.1: document added python3-libarchive-c ptest
- migration-guides/release-notes-5.1: document fixed \_test\_devtool\_add\_git\_url test
- migration-guides/release-notes-5.1: document oeqa/selftest envvars change
- migration-guides/release-notes-5.1: document spirv-tools reproducibility
- migration-guides/release-notes-5.1: fix spdx bullet point
- migration-guides/release-notes-5.1: update for several section
- migration-guides/release-notes-5.1: update release note for styhead
- migration-guides: 5.1: fix titles
- migration-guides: add release notes for 4.0.21 and 4.0.22
- oeqa/postactions: Fix archive retrieval from target
- oeqa/runtime/ssh: Fix incorrect timeout fix
- oeqa/runtime/ssh: Rework ssh timeout



- oeqa/selftest/gcc: Fix kex exchange identification error
- oeqa/selftest: Update the *BB\_HASHSERVE\_UPSTREAM*
- openssl: Fix SDK environment script to avoid unbound variable
- orc: upgrade to 0.4.40
- overview-manual: concepts: add details on package splitting
- ovmf-native: remove .pyc files from install
- package\_rpm: Check if file exists before open()
- package\_rpm: restrict rpm to 4 threads
- package\_rpm: use zstd's default compression level
- poky.conf: bump version for 5.1.1
- pseudo: Fix envp bug and add posix\_spawn wrapper
- python3-maturin: sort external libs in wheel files
- python3-setuptools: Add "python:setuptools" to *CVE\_PRODUCT*
- qemu: Fix build on musl/riscv64
- qemurunner: Clean up serial\_lock handling
- ref-manual: add missing CVE\_CHECK manifest variables
- ref-manual: add missing *EXTERNAL\_KERNEL\_DEVICETREE* variable
- ref-manual: add missing *OPKGBUILDCMD* variable
- ref-manual: add missing *TESTIMAGE\_FAILED\_QA\_ARTIFACTS*
- ref-manual: add missing image manifest variables
- ref-manual: add missing nospdx class
- ref-manual: add missing variable *PRSERV\_UPSTREAM*
- ref-manual: add mission pep517-backend sanity check
- ref-manual: add new *RECIPE\_UPGRADE\_EXTRA\_TASKS* variable
- ref-manual: add new retain class and variables
- ref-manual: add new vex class
- ref-manual: devtool-reference: document missing commands
- ref-manual: devtool-reference: refresh example outputs
- ref-manual: drop TCLIBCAPPEND variable
- ref-manual: drop siteconfig class
- ref-manual: faq: add q&a on class appends
- ref-manual: fix ordering of insane checks list

- ref-manual: merge patch-status-\* to patch-status
- ref-manual: release-process: add a reference to the doc's release
- ref-manual: release-process: refresh the current LTS releases
- ref-manual: release-process: update releases.svg
- ref-manual: release-process: update releases.svg with month after "Current"
- ref-manual: structure.rst: document missing tmp/ dirs
- ref-manual: variables: add SIGGEN\_LOCKEDSIGS\* variables
- rootfs-postcommands.bbclass: make opkg status reproducible
- scripts/install-buildtools: Update to 5.1
- selftest/sstatetests: run CDN mirror check only once
- shadow: use update-alternatives to handle groups.1
- strace: download release tarballs from GitHub
- systemd: fix broken links for sysvinit-compatible commands
- tcl: skip io-13.6 test case
- toolchain-shar-extract.sh: exit when post-relocate-setup.sh fails
- tune-cortexa32: set tune feature as armv8a
- tzdata/tzcode-native: upgrade to 2024b
- uboot-sign: fix concat\_dtb arguments
- udev-extraconf: fix network.sh script did not configure hotplugged interfaces
- util-linux: Add *findmnt* to the bash completion *RDEPENDS*
- vim: Upgrade to 9.1.0764
- virglrenderer: Add patch to fix -int-conversion build issue
- weston: Add missing runtime dependency on freerdp
- weston: backport patch to allow neatvnc < v0.9.0
- wireless-regdb: upgrade to 2024.10.07
- xserver-xorg: upgrade to 21.1.14
- xwayland: upgrade to 24.1.4

### Known Issues in Yocto-5.1.1

- N/A

## Contributors to Yocto-5.1.1

- Aditya Tayade
- Alban Bedel
- Aleksandar Nikolic
- Alexander Kanavin
- Antonin Godard
- Bruce Ashfield
- Chen Qi
- Chris Laplante
- Christian Lindeberg
- Claus Stovgaard
- Clayton Casciato
- Daniel McGregor
- Deepthi Hemraj
- Harish Sadineni
- Hiago De Franco
- Hongxu Jia
- Jagadeesh Krishnanjanappa
- Jinfeng Wang
- Jonas Gorski
- Jose Quaresma
- Joshua Watt
- Julien Stephan
- Jörg Sommer
- Kai Kang
- Katawann
- Khem Raj
- Lee Chee Yang
- Markus Volk
- Martin Jansa
- Mathieu Dubois-Briand
- Michael Opdenacker

- Mikko Rapeli
- Niko Mauno
- Ola x Nilsson
- Pavel Zhukov
- Peter Kjellerstedt
- Peter Marko
- Purushottam Choudhary
- Regis Dargent
- Richard Purdie
- Robert Yang
- Rohini Sangam
- Ross Burton
- Sergei Zhmylev
- Shunsuke Tokumoto
- Steve Sakoman
- Talel BELHAJSALEM
- Tom Hochstein
- Vijay Anusuri
- Wang Mingyu
- Yi Zhao
- Yoann Congal
- Zahir Hussain

## Repositories / Downloads for Yocto-5.1.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `styhead`
- Tag: `yocto-5.1.1`
- Git Revision: `7e081bd98fdc5435e850d1df79a5e0f1e30293d0`
- Release Artefact: `poky-7e081bd98fdc5435e850d1df79a5e0f1e30293d0`
- sha: `1ae688856bcd4aa2d1a14c2659217143cc2050151a8c194b99e6b472b0a99710`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.1/poky-7e081bd98fdc5435e850d1df79a5e0f1e30293d0.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.1/poky-7e081bd98fdc5435e850d1df79a5e0f1e30293d0.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: styhead
- Tag: yocto-5.1.1
- Git Revision: b511d0146a2e8f316f4aecc90c853215674013ea
- Release Artefact: oecore-b511d0146a2e8f316f4aecc90c853215674013ea
- sha: 71eb36bf898b3eb5a7a79c2f1c057755405740e82b21a57ac540cebc1337e151
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.1/oecore-b511d0146a2e8f316f4aecc90c853215674013ea.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.1/oecore-b511d0146a2e8f316f4aecc90c853215674013ea.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: styhead
- Tag: yocto-5.1.1
- Git Revision: 77fe18d4f8ec34501045c5d92ce7e13b1bd129e9
- Release Artefact: meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9
- sha: 4c7f8100a3675d9863e51825def3df5b263ffc81cd57bae26eedbc156d771534
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.1/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.1/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake/>
- Branch: 2.10
- Tag: yocto-5.1.1
- Git Revision: 9602a684568910fd333ffce907fa020ad3661c26
- Release Artefact: bitbake-9602a684568910fd333ffce907fa020ad3661c26
- sha: 8f5304b7a71cf7ad5dc8e5ee8bbfc041780bd402712f314d2c3c8be79c89a526
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.1/bitbake-9602a684568910fd333ffce907fa020ad3661c26.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.1/bitbake-9602a684568910fd333ffce907fa020ad3661c26.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: styhead
- Tag: yocto-5.1.1

- Git Revision: 8288c8cae7fe7303e89d8ed286de91fc26ce6cc3

## 17.6.4 Release notes for Yocto-5.1.2 (Styhead)

### Security Fixes in Yocto-5.1.2

- binutils: Fix CVE-2024-53589
- curl: Fix CVE-2024-9681
- ghostscript: Fix CVE-2024-46951, CVE-2024-46952, CVE-2024-46953, CVE-2024-46954, CVE-2024-46955 and CVE-2024-46956
- gstreamer1.0: Fix CVE-2024-47606
- gstreamer1.0-plugins-base: Fix CVE-2024-47538, CVE-2024-47541, CVE-2024-47542, CVE-2024-47600, CVE-2024-47607, CVE-2024-47615 and CVE-2024-47835
- gstreamer1.0-plugins-good: Fix CVE-2024-47537, CVE-2024-47539, CVE-2024-47540, CVE-2024-47543, CVE-2024-47544, CVE-2024-47545, CVE-2024-47546, CVE-2024-47596, CVE-2024-47597, CVE-2024-47598, CVE-2024-47599, CVE-2024-47601, CVE-2024-47602, CVE-2024-47603, CVE-2024-47606, CVE-2024-47613, CVE-2024-47774, CVE-2024-47775, CVE-2024-47776, CVE-2024-47777, CVE-2024-47778 and CVE-2024-47834
- gstreamer1.0-rtsp-server: Fix CVE-2024-44331
- libarchive: Fix CVE-2024-48957 and CVE-2024-48958
- libexpat: Fix CVE-2024-50602
- libsndfile1: Fix CVE-2024-50612
- linux-yocto/6.6: Fix CVE-2024-27059, CVE-2024-47704, CVE-2024-49863, CVE-2024-49864, CVE-2024-49866, CVE-2024-49867, CVE-2024-49868, CVE-2024-49870, CVE-2024-49871, CVE-2024-49874, CVE-2024-49875, CVE-2024-49877, CVE-2024-49878, CVE-2024-49879, CVE-2024-49881, CVE-2024-49882, CVE-2024-49883, CVE-2024-49884, CVE-2024-49886, CVE-2024-49889, CVE-2024-49890, CVE-2024-49892, CVE-2024-49894, CVE-2024-49895, CVE-2024-49896, CVE-2024-49900, CVE-2024-49901, CVE-2024-49902, CVE-2024-49903, CVE-2024-49905, CVE-2024-49907, CVE-2024-49912, CVE-2024-49913, CVE-2024-49924, CVE-2024-49925, CVE-2024-49927, CVE-2024-49929, CVE-2024-49930, CVE-2024-49931, CVE-2024-49933, CVE-2024-49935, CVE-2024-49936, CVE-2024-49937, CVE-2024-49938, CVE-2024-49939, CVE-2024-49944, CVE-2024-49946, CVE-2024-49947, CVE-2024-49948, CVE-2024-49949, CVE-2024-49950, CVE-2024-49951, CVE-2024-49952, CVE-2024-49953, CVE-2024-49954, CVE-2024-49955, CVE-2024-49957, CVE-2024-49958, CVE-2024-49959, CVE-2024-49960, CVE-2024-49961, CVE-2024-49962, CVE-2024-49963, CVE-2024-49965, CVE-2024-49966, CVE-2024-49969, CVE-2024-49973, CVE-2024-49975, CVE-2024-49976, CVE-2024-49977, CVE-2024-49978, CVE-2024-49980, CVE-2024-49981, CVE-2024-49982, CVE-2024-49983, CVE-2024-49985, CVE-2024-49986, CVE-2024-49987, CVE-2024-49988, CVE-2024-49989, CVE-2024-49991, CVE-2024-49992, CVE-2024-49995, CVE-2024-49996, CVE-2024-49997, CVE-2024-50000, CVE-2024-50001, CVE-2024-50002, CVE-2024-50003, CVE-2024-50005, CVE-2024-50006, CVE-2024-50007, CVE-2024-50008, CVE-2024-50012, CVE-2024-50013, CVE-2024-50015, CVE-2024-50016, CVE-2024-50019, CVE-2024-50022, CVE-2024-50023, CVE-2024-50024, CVE-2024-50026, CVE-2024-50029,

## 17.6. Release 5.1 (styhead) 1279

53188, CVE-2024-53200, CVE-2024-53202, CVE-2024-53208, CVE-2024-53210, CVE-2024-53213, CVE-2024-53226, CVE-2024-53227, CVE-2024-53230, CVE-2024-53231, CVE-2024-53237, CVE-2024-54683, CVE-2024-55916, CVE-2024-56369, CVE-2024-56538, CVE-2024-56551, CVE-2024-56567, CVE-2024-56572, CVE-2024-56574, CVE-2024-56577, CVE-2024-56578, CVE-2024-56579, CVE-2024-56581, CVE-2024-56593, CVE-2024-56595, CVE-2024-56596, CVE-2024-56598, CVE-2024-56600, CVE-2024-56601, CVE-2024-56602, CVE-2024-56603, CVE-2024-56604, CVE-2024-56605, CVE-2024-56606, CVE-2024-56611, CVE-2024-56613, CVE-2024-56614, CVE-2024-56615, CVE-2024-56617, CVE-2024-56622, CVE-2024-56623, CVE-2024-56626, CVE-2024-56627, CVE-2024-56629, CVE-2024-56631, CVE-2024-56634, CVE-2024-56640, CVE-2024-56642, CVE-2024-56643, CVE-2024-56648, CVE-2024-56649, CVE-2024-56650, CVE-2024-56651, CVE-2024-56653, CVE-2024-56654, CVE-2024-56657, CVE-2024-56658, CVE-2024-56659, CVE-2024-56660, CVE-2024-56662, CVE-2024-56663, CVE-2024-56664, CVE-2024-56667, CVE-2024-56670, CVE-2024-56672, CVE-2024-56675, CVE-2024-56688, CVE-2024-56689, CVE-2024-56692, CVE-2024-56694, CVE-2024-56704, CVE-2024-56708, CVE-2024-56710, CVE-2024-56715, CVE-2024-56716, CVE-2024-56717, CVE-2024-56718, CVE-2024-56720, CVE-2024-56722, CVE-2024-56723, CVE-2024-56724, CVE-2024-56725, CVE-2024-56726, CVE-2024-56727, CVE-2024-56728, CVE-2024-56729, CVE-2024-56739, CVE-2024-56741, CVE-2024-56744, CVE-2024-56745, CVE-2024-56746, CVE-2024-56747, CVE-2024-56748, CVE-2024-56751, CVE-2024-56752, CVE-2024-56754, CVE-2024-56755, CVE-2024-56756, CVE-2024-56760, CVE-2024-56763, CVE-2024-56765, CVE-2024-56767, CVE-2024-56769, CVE-2024-56770, CVE-2024-56774, CVE-2024-56776, CVE-2024-56777, CVE-2024-56778, CVE-2024-56779, CVE-2024-56780, CVE-2024-56781, CVE-2024-56783, CVE-2024-56785, CVE-2024-56786, CVE-2024-56787 and CVE-2024-57807

- qemu: Fix CVE-2024-6505
- rust: Ignore CVE-2024-43402

### Fixes in Yocto-5.1.2

- binutils: stable 2.43.1 branch update
- bitbake: runqueue: Fix performance of multiconfigs with large overlap
- bitbake: runqueue: Fix scenetask processing performance issue
- bitbake: runqueue: Optimise setscene loop processing
- build-appliance-image: Update to styhead head revision
- builder: set *CVE\_PRODUCT*
- buildtools-docs-tarball: Add rsvg so we can handle svg files in docs
- connman: Fix restart script
- contributor-guide: submit-changes.rst: suggest to remove the git signature
- cve-update-nvd2-native: Handle *BB\_NO\_NETWORK* and missing db
- cve-update-nvd2-native: Tweak to work better with NFS *DL\_DIR*
- dev-manual: bmaptool.rst: correct command for bmaptool-native
- dev-manual: bmaptool.rst: simplify and fix instructions
- dev-manual: fix styling of references to bmaptool



- dnf: drop python3-iniparse from *DEPENDS* and *RDEPENDS*
- do\_package/sstate/sstatesig: Change timestamp clamping to hash output only
- docs: Gather dependencies in poky.yaml.in
- docs: Update the documentation for *SRCPV*
- docs: standards.md: add a section on admonitions
- docs: update current releases
- expat: upgrade to 2.6.4
- gcc: Fix c++; tweak for Wrangle-loop-construct
- ghostscript: upgrade 10.04.0
- glibc: stable 2.40 branch updates.
- groff: Fix race issues for parallel build
- gstreamer1.0-libav: explicitly disable documentation
- gstreamer1.0: run ptests in parallel
- gstreamer1.0: upgrade to 1.24.10
- linux-yocto/6.6: bsp/genericarm64: disable ARM64\_SME
- linux-yocto/6.6: genericarm64.cfg: enable CONFIG\_DMA\_CMA
- linux-yocto/6.6: update to v6.6.69
- ltng-modules: fix sched\_stat\_runtime changed in Linux 6.6.66
- migration-guides: add release notes for 4.0.23, 5.0.4, 5.0.5 and 5.1.1
- oeqa/ssh: Improve performance and log sizes
- oeqa/utis/gitarchive: Return tag name and improve exclude handling
- poky.conf: add new tested distros
- poky.conf: bump version for 5.1.2
- poky.yaml.in: add missing locales dependency
- poky.yaml.in: replace inkscape dependency by librsvg2-bin
- populate\_sdk\_ext: write\_local\_conf add shutil import
- python3-poetry-core: drop python3-six from *RDEPENDS*
- python3: upgrade to 3.12.8
- ref-manual: SSTATE\_MIRRORS/SOURCE\_MIRROR\_URL: add instructions for mirror authentication
- ref-manual: classes: fix bin\_package description
- ref-manual: devtool-reference: add warning note on deploy-target and shared objects
- ref-manual: merge two separate descriptions of *RECIPE\_UPGRADE\_EXTRA\_TASKS*

- ref-manual: move runtime-testing section to the test-manual
- ref-manual: packages: move ptest section to the test-manual
- ref-manual: qa-checks: remove patch-status-core/patch-status-noncore
- ref-manual: use standardized method accross both ubuntu and debian for locale install
- reproducible-builds.rst: show how to build a single package
- resulttool: Add --logfile-archive option to store mode
- resulttool: Allow store to filter to specific revisions
- resulttool: Clean up reproducible build logs
- resulttool: Fix passthrough of --all files in store mode
- resulttool: Handle ltp rawlogs as well as ptest
- resulttool: Improve repo layout for oeselftest results
- resulttool: Trim the precision of duration information
- resulttool: Use single space indentation in json output
- rxvt-unicode.inc: disable the terminfo installation by setting TIC to :
- selftest/reproducible: Clean up pathnames
- selftest/reproducible: Drop rawlogs
- shadow: use update-alternatives to handle su.1 and nologin.8
- system-requirements.rst: add dependencies for pdf builds
- system-requirements: add fedora 39 to supported distros
- system-requirements: update list of supported distros
- systemd-boot: drop intltool-native from *DEPENDS*
- systemd: drop intltool-native from *DEPENDS*

### Known Issues in Yocto-5.1.2

- N/A

### Contributors to Yocto-5.1.2

Thanks to the following people who contributed to this release:

- Alexander Kanavin
- Antonin Godard
- Bruce Ashfield
- Changqing Li
- Deepthi Hemraj
- Guénaél Muller

- Guðni Már Gilbert
- Hitendra Prajapati
- Lee Chee Yang
- Mark Hatle
- Michael Nazzareno Trimarchi
- Michael Opdenacker
- Peter Marko
- Richard Purdie
- Robert Yang
- Ross Burton
- Sid-Ali
- Steve Sakoman
- Sunil Dora
- Trevor Gamblin
- Wang Mingyu
- Xiangyu Chen
- Yash Shinde

## Repositories / Downloads for Yocto-5.1.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `styhead`
- Tag: `yocto-5.1.2`
- Git Revision: `ff9ca74e170480578fdb1f7bcd897f0e69e46a5`
- Release Artefact: `poky-ff9ca74e170480578fdb1f7bcd897f0e69e46a5`
- sha: `3c8d5504ebc988a6427e31d3a9e84e74f16f84b7e9b0884f77be6bd6231b7fef`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.2/poky-ff9ca74e170480578fdb1f7bcd897f0e69e46a5.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.2/poky-ff9ca74e170480578fdb1f7bcd897f0e69e46a5.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `styhead`
- Tag: `yocto-5.1.2`
- Git Revision: `62dfe689246d648f9970a5476716e486b1a33765`

- Release Artefact: oecore-62dfe689246d648f9970a5476716e486b1a33765
- sha: 8118c0260e673dbf9f3d7cd0a6d8364fc337f3e8ff75f0c449be88d2157e78fb
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.2/oecore-62dfe689246d648f9970a5476716e486b1a33765.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.2/oecore-62dfe689246d648f9970a5476716e486b1a33765.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: styhead
- Tag: yocto-5.1.2
- Git Revision: 77fe18d4f8ec34501045c5d92ce7e13b1bd129e9
- Release Artefact: meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9
- sha: 4c7f8100a3675d9863e51825def3df5b263ffc81cd57bae26eedbc156d771534
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.2/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.2/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.10
- Tag: yocto-5.1.2
- Git Revision: 1452e74cc4ddfaadc6537a049877a66cec253c8d
- Release Artefact: bitbake-1452e74cc4ddfaadc6537a049877a66cec253c8d
- sha: 26538d0b8ab907d962623707697bfc6826615239a724b1805e0c3acbd74fdcaa
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.2/bitbake-1452e74cc4ddfaadc6537a049877a66cec253c8d.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.2/bitbake-1452e74cc4ddfaadc6537a049877a66cec253c8d.tar.bz2>

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: styhead
- Tag: yocto-5.1.2
- Git Revision: 8ac3e2eb1dd4149b24af03666813dc6d94df466d

## 17.6.5 Release notes for Yocto-5.1.3 (Styhead)

### Security Fixes in Yocto-5.1.3

- go: Fix CVE-2024-45336, CVE-2024-45341 and CVE-2025-22866
- linux-yocto/6.6: Fix CVE-2024-36476, CVE-2024-53179, CVE-2024-56582, CVE-2024-56703, CVE-2024-57801, CVE-2024-57802, CVE-2024-57841, CVE-2024-57882, CVE-2024-57887, CVE-2024-57890, CVE-2024-57892, CVE-2024-57895, CVE-2024-57896, CVE-2024-57900, CVE-2024-57901, CVE-2024-57902, CVE-2024-57906, CVE-2024-57907, CVE-2024-57908, CVE-2024-57910, CVE-2024-57911, CVE-2024-57912, CVE-2024-57913, CVE-2024-57916, CVE-2024-57922, CVE-2024-57925, CVE-2024-57926, CVE-2024-57933, CVE-2024-57938, CVE-2024-57939, CVE-2024-57940, CVE-2024-57949, CVE-2024-57951, CVE-2025-21631, CVE-2025-21636, CVE-2025-21637, CVE-2025-21638, CVE-2025-21639, CVE-2025-21640, CVE-2025-21642, CVE-2025-21652, CVE-2025-21658, CVE-2025-21665, CVE-2025-21666, CVE-2025-21667, CVE-2025-21669, CVE-2025-21670, CVE-2025-21671, CVE-2025-21673, CVE-2025-21674, CVE-2025-21675, CVE-2025-21676, CVE-2025-21680, CVE-2025-21681, CVE-2025-21683, CVE-2025-21684, CVE-2025-21687, CVE-2025-21689, CVE-2025-21690, CVE-2025-21692, CVE-2025-21694, CVE-2025-21697 and CVE-2025-21699
- python3: Fix CVE-2024-12254, CVE-2025-0938 and 3 other vulnerabilities (gh-80222, gh-119511 and gh-126108).
- socat: Fix CVE-2024-54661
- vim: Fix CVE-2025-22134 and CVE-2025-24014

### Fixes in Yocto-5.1.3

- bitbake: bblayers/query: Fix using "removeprefix" string method
- bitbake: cooker: Make cooker 'skiplist' per-multiconfig/mc
- bitbake: tests/fetch: Fix git shallow test failure with git >= 2.48
- boost: fix do\_fetch error
- build-appliance-image: Update to styhead head revision
- classes/nativesdk: also override *TUNE\_PKGARCH*
- classes/qemu: use tune to select QEMU\_EXTRAOPTIONS, not package architecture
- cmake: apply parallel build settings to ptest tasks
- contributor-guide/submit-changes: add policy on AI generated code
- cve-check: fix cvesInRecord
- cve-check: restore CVE\_CHECK\_SHOW\_WARNINGS functionality
- dev-manual/building: document the initramfs-framework recipe
- devtool: ide-sdk recommend *DEBUG\_BUILD*
- devtool: ide-sdk remove the plugin from eSDK installer
- devtool: ide-sdk sort cmake preset

- devtool: modify support debug-builds
- docs: Add favicon for the documentation html
- docs: Fix typo in standards.md
- docs: Update autobuilder URLs to valkyrie
- enchant2: correct *SRC\_URI* and other uris
- go: upgrade to 1.22.12
- libnsl2: set *CVE\_PRODUCT*
- libxml-parser-perl: correct *SRC\_URI*
- linux-yocto/6.6: update to v6.6.75
- linux: Modify kernel configuration to fix runqlat issue
- lrzsz: update *SRC\_URI* to avoid redirect
- migration-guides: add release notes for 4.0.24, 5.0.6, 5.0.7 and 5.1.2
- oe-selftest: devtool ide-sdk use modify debug-build
- oeqa/gitarchive: Fix syntax warning
- poky.conf: bump version for 5.1.3
- python3: upgrade 3.12.9
- ref-manual/faq: add q&a on systemd as default
- resulttool/store: Fix permissions of logarchive
- rust-target-config: Fix TARGET\_C\_INT\_WIDTH with correct size
- scripts/install-buildtools: Update to 5.1.2
- sdk-manual: extensible.rst: devtool ide-sdk improve
- sdk-manual: extensible.rst: update devtool ide-sdk
- systemd: set *CVE\_PRODUCT*
- test-manual/ptest: link to common framework ptest classes
- test-manual/reproducible-builds: fix reproducible links
- vim: Upgrade 9.1.1043

### Known Issues in Yocto-5.1.3

- N/A

### Contributors to Yocto-5.1.3

- Adrian Freihofer
- Aleksandar Nikolic
- Alexander Kanavin
- Antonin Godard
- Bruce Ashfield
- Chris Laplante
- Divya Chellam
- Harish Sadineni
- Jiaying Song
- Joerg Schmidt
- Lee Chee Yang
- Mikko Rapeli
- Peter Marko
- Richard Purdie
- Ross Burton
- Simon A. Eugster
- Steve Sakoman

### Repositories / Downloads for Yocto-5.1.3

#### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [styhead](#)
- Tag: [yocto-5.1.3](#)
- Git Revision: [11a8dec6e29ac0b2fd942c0fc00dd7fc30658841](#)
- Release Artefact: [poky-11a8dec6e29ac0b2fd942c0fc00dd7fc30658841](#)
- sha: [9ebcacaab53058fd97b06134e06b5883df3c7ddb25dae43a2f3809c4f65d24b5](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.3/poky-11a8dec6e29ac0b2fd942c0fc00dd7fc30658841.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.3/poky-11a8dec6e29ac0b2fd942c0fc00dd7fc30658841.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [styhead](#)
- Tag: [yocto-5.1.3](#)

- Git Revision: [35ffa0ed523ba95f069dff5b7df3f819ef031015](#)
- Release Artefact: [oecore-35ffa0ed523ba95f069dff5b7df3f819ef031015](#)
- sha: [67efedf0afa9ac9e4664f02923a4c5c2429f2f1be697e39f9cbffb9e3f2d9d2c](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.3/oecore-35ffa0ed523ba95f069dff5b7df3f819ef031015.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.3/oecore-35ffa0ed523ba95f069dff5b7df3f819ef031015.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [styhead](#)
- Tag: [yocto-5.1.3](#)
- Git Revision: [77fe18d4f8ec34501045c5d92ce7e13b1bd129e9](#)
- Release Artefact: [meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9](#)
- sha: [4c7f8100a3675d9863e51825def3df5b263ffc81cd57bae26eedbc156d771534](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.3/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.3/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.10](#)
- Tag: [yocto-5.1.3](#)
- Git Revision: [58e5c70a0572ff5994dc181694e05cd5d3ddaf66](#)
- Release Artefact: [bitbake-58e5c70a0572ff5994dc181694e05cd5d3ddaf66](#)
- sha: [8b1d8aa3de6ca8c520f1b528e342e06de0cff918a11d77862c499185a9ba8fec](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.3/bitbake-58e5c70a0572ff5994dc181694e05cd5d3ddaf66.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.3/bitbake-58e5c70a0572ff5994dc181694e05cd5d3ddaf66.tar.bz2>

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [styhead](#)
- Tag: [yocto-5.1.3](#)
- Git Revision: [fd9c744d6e73a5719e61a3c0063b1602ca386e91](#)



## 17.6.6 Release notes for Yocto-5.1.4 (Styhead)

### Security Fixes in Yocto-5.1.4

- binutils: Fix CVE-2025-0840
- grub: Fix CVE-2024-45774, CVE-2024-45775, CVE-2024-45776, CVE-2024-45777, CVE-2024-45778, CVE-2024-45779, CVE-2024-45780, CVE-2024-45781, CVE-2024-45782, CVE-2024-45783, CVE-2024-56737, CVE-2025-0622, CVE-2025-0624, CVE-2025-0677, CVE-2025-0678, CVE-2025-0684, CVE-2025-0685, CVE-2025-0686, CVE-2025-0689, CVE-2025-0690, CVE-2025-1118 and CVE-2025-1125
- libtasn1: fix CVE-2024-12133
- libxml2: fix CVE-2024-56171, CVE-2025-24928 and CVE-2025-27113
- openssh: Fix CVE-2025-26465 and CVE-2025-26466
- puzzles: Ignore CVE-2024-13769, CVE-2024-13770 and CVE-2025-0837
- subversion: Ignore CVE-2024-45720
- xserver-xorg: Fix CVE-2025-26594, CVE-2025-26595, CVE-2025-26596, CVE-2025-26597, CVE-2025-26598, CVE-2025-26599, CVE-2025-26600 and CVE-2025-26601
- xwayland: Fix CVE-2025-26594, CVE-2025-26595, CVE-2025-26596, CVE-2025-26597, CVE-2025-26598, CVE-2025-26599, CVE-2025-26600 and CVE-2025-26601

### Fixes in Yocto-5.1.4

- bitbake: event/utis: Avoid deadlock from lock\_timeout() and recursive events
- bitbake: utis: Add signal blocking for lock\_timeout
- bitbake: utis: Print information about lock issue before exiting
- bitbake: utis: Tweak lock\_timeout logic
- build-appliance-image: Update to styhead head revision
- docs: Remove all mention of core-image-lsb
- grub: backport strlcpy function
- grub: drop obsolete CVE statuses
- icu: Adjust ICU\_DATA\_DIR path on big endian targets
- libtasn1: upgrade to 4.20.0
- libxml2: upgrade to 2.13.6
- migration-guides: add release notes for 4.0.25 and 5.1.3
- poky.conf: bump version for 5.1.4
- ref-manual: Add missing variable *IMAGE\_ROOTFS\_MAXSIZE*
- ref-manual: don't refer to poky-lsb
- ref-manual: remove OE\_IMPORTS

- tzcode-native: Fix compiler setting from 2023d version
- tzdata/tzcode-native: upgrade to 2025a
- vulnerabilities/classes: remove references to cve-check text format
- xserver-xf86-config: add a configuration fragment to disable screen blanking
- xserver-xf86-config: remove obsolete configuration files
- xserver-xorg: upgrade to 21.1.16
- xwayland: upgrade to 21.1.6

### Known Issues in Yocto-5.1.4

- NA

### Contributors to Yocto-5.1.4

Thanks to the following people who contributed to this release:

- Alessio Cascone
- Lee Chee Yang
- Makarios Christakis
- Marta Rybczynska
- Peter Marko
- Priyal Doshi
- Richard Purdie
- Ross Burton
- Steve Sakoman
- Vijay Anusuri
- Wang Mingyu
- Weisser, Pascal

### Repositories / Downloads for Yocto-5.1.4

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [styhead](#)
- Tag: [yocto-5.1.4](#)
- Git Revision: [70dc28ac287bf35541270cae1d99130a0f6b7b5f](#)
- Release Artefact: [poky-70dc28ac287bf35541270cae1d99130a0f6b7b5f](#)
- sha: [63f1d3d47a28bd9b41c89db6e1f2657c04233a00d10210795e766c0bc265d766](#)

- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.4/poky-70dc28ac287bf35541270cae1d99130a0f6b7b5f.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.4/poky-70dc28ac287bf35541270cae1d99130a0f6b7b5f.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: styhead
- Tag: yocto-5.1.4
- Git Revision: 2d94f4b8a852dc761f89e5106347e239382df5fb
- Release Artefact: oecore-2d94f4b8a852dc761f89e5106347e239382df5fb
- sha: 344ac23f814c049d69b06cee42c43b7b422506ce84397406caef09becb2555bf
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.4/oecore-2d94f4b8a852dc761f89e5106347e239382df5fb.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.4/oecore-2d94f4b8a852dc761f89e5106347e239382df5fb.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: styhead
- Tag: yocto-5.1.4
- Git Revision: 77fe18d4f8ec34501045c5d92ce7e13b1bd129e9
- Release Artefact: meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9
- sha: 4c7f8100a3675d9863e51825def3df5b263ffc81cd57bae26eedbc156d771534
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.4/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.4/meta-mingw-77fe18d4f8ec34501045c5d92ce7e13b1bd129e9.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.10
- Tag: yocto-5.1.4
- Git Revision: 82b9f42126983579da03bdbb4e3ebf07346118a7
- Release Artefact: bitbake-82b9f42126983579da03bdbb4e3ebf07346118a7
- sha: 209d62c5262f2287af60e7fe2343c29ab25b5088de4da71de89016e75900285a
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.1.4/bitbake-82b9f42126983579da03bdbb4e3ebf07346118a7.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.1.4/bitbake-82b9f42126983579da03bdbb4e3ebf07346118a7.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>

- Branch: `styhead`
- Tag: `yocto-5.1.4`
- Git Revision: `f0324b8f14881227336f84325cdebd0518e17796`

## 17.7 Release 5.0 (scarthgap)

### 17.7.1 Release 5.0 LTS (scarthgap)

#### Migration notes for 5.0 (scarthgap)

This section provides migration information for moving to the Yocto Project 5.0 Release (codename "scarthgap") from the prior release.

To migrate from an earlier LTS release, you **also** need to check all the previous migration notes from your release to this new one:

- *Release 4.3 (nanbield)*
- *Release 4.2 (mickledore)*
- *Release 4.1 (langdale)*
- *Release 4.0 (kirkstone)*
- *Migration notes for 3.4 (honister)*
- *Release 3.3 (hardknott)*
- *Release 3.2 (gatesgarth)*

#### Supported kernel versions

The `OLDEST_KERNEL` setting is still "5.15" in this release, meaning that out the box, older kernels are not supported. See *4.3 migration notes* for details.

#### Supported distributions

Compared to the previous releases, running BitBake is supported on new GNU/Linux distributions:

- Rocky 9

On the other hand, some earlier distributions are no longer supported:

- Fedora 37
- Ubuntu 22.10
- OpenSUSE Leap 15.3

See *all supported distributions*.

## Go language changes

The `linkmode` flag was dropped from `GO_LDFLAGS` for `nativesdk` and `cross-canadian`. Also, dynamic linking was disabled for the whole set of (previously) supported architectures in the `goarch` class.

## systemd changes

Systemd's nss-resolve plugin is now supported and can be added via the `nss-resolve` *PACKAGECONFIG* option, which is from now on required (along with `resolved`) by the `systemd-resolved` feature. Related to that (i.e., Systemd's network name resolution), an option to use `stub-resolv.conf` was added as well.

## Recipe changes

- Runtime testing of `pptest` now fails if no test results are returned by any given `pptest`.

## Deprecated variables

- `CVE_CHECK_IGNORE` should be replaced with *CVE\_STATUS*

## Removed variables

The following variables have been removed:

- `DEPLOY_DIR_TAR`: no longer needed since the `package_tar` class was removed in 4.2.
- `PYTHON_PN`: Python 2 has previously been removed, leaving Python 3 as the sole major version. Therefore, this abstraction to differentiate both versions is no longer needed.
- `oldincludedir`
- `USE_L10N`: previously deprecated, and now removed.
- `CVE_SOCKET_TIMEOUT`
- `SERIAL_CONSOLES_CHECK` - use *SERIAL\_CONSOLES* instead as all consoles specified in the latter are checked for their existence before a `getty` is started.

## Removed recipes

The following recipes have been removed in this release:

- `libcroco`: deprecated and archived by the Gnome Project.
- `liberror-perl`: unmaintained and no longer needed - moved to `meta-perl`.
- `linux-yocto`: version 6.1 (version 6.6 provided instead).
- `systemtap-uprobes`: obsolete.
- `zvariant`: fails to build with newer Rust.

## Removed classes

No classes have been removed in this release.

## QEMU changes

In `tune-core2`, the `cpu` models `n270` and `core2duo` are no longer passed to QEMU, since its documentation recommends not using them with `-cpu` option. Therefore, from now on, `Nehalem` model is used instead.

## ipk packaging changes

`ipk` packaging (using `opkg`) now uses `zstd` compression instead of `xz` for better compression and performance. This does mean that `.ipk` packages built using the 5.0 release requires `Opkg` built with `zstd` enabled --- naturally this is the case in 5.0, but at least by default these packages will not be usable on older systems where `Opkg` does not have `zstd` enabled at build time.

Additionally, the internal dependency solver in `Opkg` is now deprecated --- it is still available in this release but will trigger a warning if selected. The default has been the external `libsolv` solver for some time, but if you have explicitly removed that from `PACKAGECONFIG` for `Opkg` to select the internal solver, you should plan to switch to `libsolv` in the near future (by including `libsolv` your custom `PACKAGECONFIG` value for `Opkg`, or reverting to the default value).

## motd message when using `DISTRO = "poky"`

The default `poky` *DISTRO* is explicitly a *reference* distribution for testing and development purposes. It enables most hardware and software features so that they can be tested, but this also means that from a security point of view the attack surface is very large.

We encourage anyone using the Yocto Project for production use to create their own distribution and not use Poky. To encourage this behaviour further, in 5.0 a warning has been added to `/etc/motd` when Poky is used so that the developer will see it when they log in. If you are creating your own distribution this message will not show up.

For information on how to create your own distribution, see "[Creating Your Own Distribution](#)".

## Miscellaneous changes

- `bitbake-whatchanged` script was removed as it was broken and unmaintained.
- `scripts/sstate-cache-management.sh` has been replaced by `scripts/sstate-cache-management.py`, a more performant Python-based version.
- The `bmap-tools` recipe has been renamed to `bmactool`.
- `gpgme` has had Python binding support disabled since upstream does not support Python 3.12 yet. This will be fixed in future once it is fixed upstream.)
- A warning will now be shown if the `virtual/` prefix is used in runtime contexts (*RDEPENDS* / *RPROVIDES*) --- See *virtual-slash* for details.
- `recipetool` now prefixes the names of recipes created for Python modules with `python3-`.

- The `cve-check` class no longer produces a warning for remote patches --- it only logs a note and does not try to fetch the patch in order to scan it for issues or CVE numbers. However, CVE number references in remote patch file names will now be picked up.
- The values of `PE` and `PR` have been dropped from `-f{file,macro,debug}-prefix-map`, in order to avoid unnecessary churn in debugging symbol paths when the version is bumped. This is unlikely to cause issues, but if you are paying attention to the debugging source path (e.g. in recipes that need to manipulate these files during packaging) then you will notice the difference. A new `TARGET_DBGSRC_DIR` variable is provided to make this easier.
- `ccache` no longer supports FORTRAN.

## 17.7.2 Release notes for 5.0 (scarthgap)

### New Features / Enhancements in 5.0

- Linux kernel 6.6, gcc 13.2, glibc 2.39, LLVM 18.1, and over 300 other recipe upgrades
- New variables:
  - `CVE_DB_INCR_UPDATE_AGE_THRES`: Configure the maximum age of the internal CVE database for incremental update (instead of a full redownload).
  - `RPMBUILD_EXTRA_PARAMS`: support extra user-defined fields without crashing the RPM package creation.
  - `OPKG_MAKE_INDEX_EXTRA_PARAMS`: support extra parameters for `opkg-make-index`.
  - `EFI_UKI_PATH`, `EFI_UKI_DIR`: define the location of UKI image in the EFI System partition.
  - `TARGET_DBGSRC_DIR`: specifies the target path to debug source files
  - `USERADD_DEPENDS`: provides a way to declare dependencies on the users and/or groups created by other recipes, resolving a long-standing build ordering issue
- Architecture-specific enhancements:
  - `genericarm64`: a new `MACHINE` to represent a 64-bit General Arm SystemReady platform.
  - Add Power8 tune to PowerPC architecture.
  - `arch-armv9`: remove CRC and SVE tunes, since FEAT\_CRC32 is now mandatory and SVE/SVE2 are enabled by default in GCC's `-march=armv9-a`.
  - `arm/armv*`: add all of the additional Arm tunes in GCC 13.2.0
- Kernel-related enhancements:
  - The default kernel is the current LTS (6.6).
  - Add support for `genericarm64`.
- New core recipes:
  - `bmaptool`: a tool for creating block maps for files and flashing images, being now under the Yocto Project umbrella.

- `core-image-initramfs-boot`: a minimal initramfs image, containing just `udev` and `init`, designed to find the main root filesystem and pivot to it.
  - `lzlib`: a data compression library that provides LZMA compression and decompression functions.
  - `lzop`: a compression utility based on the LZO library, that was brought back after a (now reverted) removal.
  - `python3-jsonschema-specifications`: support files for JSON Schema Specifications (meta-schemas and vocabularies), added as a new dependency of `python3-jsonschema`.
  - `python3-maturin`: a project that allows building and publishing Rust crates as Python packages.
  - `python3-meson-python`: a Python build backend that enables the Meson build-system for Python packages.
  - `python3-pyproject-metadata`: a class to handle PEP 621 metadata, and a dependency for `python3-meson-python`.
  - `python3-referencing`: another dependency of `python3-jsonschema`, it provides an implementation of JSON reference resolution.
  - `python3-rpds-py`: Python bindings to the Rust `rpds` crate, and a runtime dependency for `python3-referencing`.
  - `python3-sphinxcontrib-jquery`: a Sphinx extension to include jQuery on newer Sphinx releases. Recent versions of `python3-sphinx-rtd-theme` depend on it.
  - `python3-websockets`: a library for building WebSocket servers and clients in Python.
  - `python3-yamllint`: a linter for YAML files. In U-Boot, the `binman` tool uses this linter to verify the configurations at compile time.
  - `systemd-boot-native`: a UEFI boot manager, this time built as native to provide the `ukify` tool.
  - `utfcpp`: a C++ library to handle UTF-8 encoded strings. It was added as a dependency for `taglib` after its upgrade to v2.0.
  - `vulkan-utility-libraries`: a set of libraries to share code across various Vulkan repositories.
  - `vulkan-volk`: a meta-loader for Vulkan, needed to support building the latest `vulkan-tools`.
- QEMU / `runqemu` enhancements:
    - QEMU has been upgraded to version 8.2.1
    - `qemuboot`: support predictable network interface names.
    - `runqemu`: match ".rootfs." in addition to "-image-" for the root filesystem.
    - `cmake-qemu`: a new class allowing to execute cross-compiled binaries using QEMU user-mode emulation.
  - Rust improvements:
    - Rust has been upgraded to version 1.75
    - The Rust profiler (i.e., PGO - Profile-Guided Optimization) options were enabled back.
    - The Rust `oe-selftest` were enabled, except for `mips32` whose tests are skipped.



- `rust-cross-canadian`: added `riscv64` to cross-canadian hosts.
- wic Image Creator enhancements:
  - Allow the imager's output file extension to match the imager's name, instead of hardcoding it to `direct` (i.e., the default imager)
  - For GPT-based disks, add reproducible Disk GUID generation
  - Allow generating reproducible ext4 images
  - Add feature to fill a specific range of a partition with zeros
  - `bootimg-efi`: add `install-kernel-into-boot-dir` parameter to configure kernel installation point(s) (i.e., rootfs and/or boot partition)
  - `rawcopy`: add support for `zstd` decompression
- SDK-related improvements:
  - `nativesdk`: let `MACHINE_FEATURES` be set by `machine-sdk` configuration files.
  - `nativesdk`: prevent `MACHINE_FEATURES` and `DISTRO_FEATURES` from being backfilled.
  - Support for `riscv64` as an SDK host architecture
  - Extend recipes to `nativesdk`: `acpica`, `libpcap`, `python3-setuptools-rust`
- Testing:
  - Move `patchtest` to the core (as `scripts/patchtest`, test cases under `meta/lib/patchtest/tests`) and make a number of improvements to enable it to validate patches submitted on the mailing list again. Additionally, make it work with the original upstream version of `Patchwork`.
  - Add an optional `unimplemented-ptest` QA warning to detect upstream packages with tests, that do not use `ptest`.
  - `testimage`: retrieve the `ptests` directory, especially for the logs, upon `ptest` failure.
  - `oeqa`, `oe-selftest`: add test cases for Maturin (SDK and runtime).
  - Proof-of-concept of screenshot-based runtime UI test (`meta/lib/oeqa/runtime/cases/login.py`)
  - Enable `ptests` for `python3-attrs`, `python3-pyyaml`, `xz`
- Utility script changes:
  - `oe-init-build-env` can generate a initial configuration (`.vscode`) for VSCode and its "Yocto Project BitBake" extension.
  - The `sstate-cache-management` script has been rewritten in `python` for better performance and maintainability
  - `bitbake-layers`: added an option to update the reference of repositories in layer setup
- BitBake improvements:
  - New `inherit_defer` statement which works as `inherit` does, except that it is only evaluated at the end of parsing --- recommended where a conditional expression is used, e.g.:

```
inherit_defer ${@bb.utils.contains('PACKAGECONFIG', 'python',  
↪ 'python3targetconfig', '', d)}
```

This allows conditional expressions to be evaluated 'late' meaning changes to the variable after the line is parsed will take effect - with inherit this is not the case.

- Add support for *BB\_LOADFACTOR\_MAX*, so Bitbake can stop running extra tasks if the system load is too high, especially in distributions where `/proc/pressure` is disabled.
- `taskexp_ncurses`: add ncurses version of `taskexp`, the dependency explorer originally implemented with GTK.
- Improve `runqueue` performance by adding a cache mechanism in `build_taskdepdata`.
- `bitbake.conf`: add `runtime_dir` to represent the path to the runtime state directory (i.e., `/run`).
- Allow to disable colored text output through the `NO_COLOR` environment variable.
- `git-make-shallow` script: add support for Git's `safe.bareRepository=explicit` configuration setting.
- Hash equivalence gained a number of scalability improvements including:
  - \* Support for a wide range of database backends through *SQLAlchemy*
  - \* Support for hash equivalence server and client to communicate over websockets
  - \* Support for per-user permissions in the hashserver, and on the client side specifying credentials via the environment or `.netrc`
  - \* Add garbage collection to remove unused unihashes from the database.
- devtool improvements:
  - Introduce a new `ide-sdk` plugin to generate a configuration to use the eSDK through an IDE.
  - Add `--no-pypi` option for Python projects that are not hosted on PyPI.
  - Add support for Git submodules.
  - `ide:vscode`: generate files from recipe sysroots and debug the root filesystem in read-only mode to avoid confusion.
  - `modify`: add support for multiple sources in *SRC\_URI*.
  - Support plugins within plugins.
- recipetool improvements:
  - `appendsrcfile(s)`: add a mode to update the recipe itself.
  - `appendsrcfile(s)`: add `--dry-run` mode.
  - `create`: add handler to create Go recipes.
  - `create`: improve identification of licenses.
  - `create`: add support for modern Python PEP-517 build systems including hatchling, maturin, meson-python.

- create: add PyPi support.
- create: prefix created Python recipes with `python3-`.
- Packaging changes:
  - `package_rpm`: the RPM package compressor's mode can now be overridden.
  - ipk packaging (using `opkg`) now uses `zstd` compression instead of `xz` for better compression and performance.
- Security improvements:
  - Improve incremental CVE database download from NVD. Rejected CVEs are removed, configuration is kept up-to-date. The age threshold for incremental update can be configured with `CVE_DB_INCR_UPDATE_AGE_THRES` variable.
- Toaster Web UI improvements:
  - Numerous bugfixes, and additional input validation
  - Add `pytest` support and add/update test cases
- Prominent documentation updates:
  - Documentation for using the new `devtool ide-sdk` command and features. See *Using devtool in Your SDK Workflow* for details.
  - New "Variable Context" section in the BitBake User Manual.
  - New `make stylecheck` command to run *Vale*, to perform text style checks and comply with text writing standards in the industry.
  - New `make sphinx-lint` command to run *sphinx-lint*. After customization, this will allow us to enforce Sphinx syntax style choices.
- Miscellaneous changes:
  - Systemd's following *PACKAGECONFIG* options were added: `cryptsetup-plugins`, `no-ntp-fallback`, and `p11kit`.
  - New *PACKAGECONFIG* options added to `libarchive`, `libinput`, `libunwind`, `mesa`, `mesa-gl`, `openssh`, `perf`, `python3-pyaml`, `qemu`, `rpm`, `shadow`, `strace`, `syslinux`, `systemd`, `vte`, `webkitgtk`, `xserver-xorg`.
  - `systemd-boot` can, from now on, be compiled as `native`, thus providing `ukify` tool to build UKI images.
  - `systemd`: split bash completion for `udevadm` in a new `udev-bash-completion` package.
  - The *go-vendor* class was added to support offline builds (i.e., vendoring). It can also handle modules from the same repository, taking into account their versions.
  - Disable `strace` support of bluetooth by default.
  - `openssh` now has a `systemd` service: `sshd.service`.
  - The *python\_mesonpy* class was added (moved in from `meta-python`) to support Python package builds using the `meson-python` PEP-517 build backend.

- Support for unpacking .7z archives in *SRC\_URI* using p7zip.
- Add minimal VS Code configuration to avoid VS Code's indexer from choking on build directories.

### Known Issues in 5.0

- gpgme has had Python binding support disabled since upstream does not yet support Python 3.12.

### Recipe License changes in 5.0

The following corrections have been made to the *LICENSE* values set by recipes:

- elfutils: split license for libraries & backend and utilities.
- ghostscript: correct *LICENSE* to AGPL-3.0-or-later.
- kbd: update license for consolefont and keymaps.
- libsystemd: set its own *LICENSE* value (LGPL-2.1-or-later) to add more granularity.
- libtest-warnings-perl: update *LICENSE* Artistic-1.0 to Artistic-1.0-Perl.
- linux-firmware: set package *LICENSE* appropriately for carl9170, rockchip and powerpr.
- newlib: add license Apache-2.0-with-LLVM-exception.
- python3-poetry-core: add license BSD-3-Clause for fastjsonschema.
- systemd: make the scope of LGPL more accurate (LGPL-2.1 -> LGPL-2.1-or-later).
- util-linux: add GPL-1.0-or-later license for fdisk and MIT license for flock.
- zstd: set to dual-licensed BSD-3-Clause or GPL-2.0-only.

### Security Fixes in 5.0

- avahi: CVE-2023-1981, CVE-2023-38469, CVE-2023-38470, CVE-2023-38471, CVE-2023-38469, CVE-2023-38470, CVE-2023-38471, CVE-2023-38472, CVE-2023-38473
- bind: CVE-2023-4408, CVE-2023-5517, CVE-2023-5679, CVE-2023-50387
- bluez5: CVE-2023-45866
- coreutils: CVE-2024-0684
- cups: CVE-2023-4504
- curl: CVE-2023-46218
- expat: CVE-2024-28757
- gcc: CVE-2023-4039
- glibc: CVE-2023-5156, CVE-2023-0687
- gnutils: CVE-2024-0553, CVE-2024-0567, CVE-2024-28834, CVE-2024-28835
- go: CVE-2023-45288
- grub: CVE-2023-4692, CVE-2023-4693

- grub2: CVE-2023-4001 (ignored), CVE-2024-1048 (ignored)
- libgit2: CVE-2024-24575, CVE-2024-24577
- libsndfile1: CVE-2022-33065
- libssh2: CVE-2023-48795
- libuv: CVE-2024-24806
- libxml2: CVE-2023-45322 (ignored)
- linux-yocto/6.6: CVE-2020-16119
- openssh: CVE-2023-48795, CVE-2023-51384, CVE-2023-51385
- openssl: CVE-2023-5363, CVE-2023-5678, CVE-2023-6129, CVE-2023-6237, CVE-2024-0727, CVE-2024-2511
- perl: CVE-2023-47100
- pixman: CVE-2023-37769 (ignored)
- python3-cryptography{-vectors}: CVE-2023-49083, CVE-2024-26130
- python3-urllib3: CVE-2023-45803
- shadow: CVE-2023-4641
- sudo: CVE-2023-42456
- tiff: CVE-2023-6228, CVE-2023-6277, CVE-2023-52355, CVE-2023-52356
- vim: CVE-2023-46246, CVE-2023-48231, CVE-2023-48232, CVE-2023-48233, CVE-2023-48234, CVE-2023-48235, CVE-2023-48236, CVE-2023-48237, CVE-2024-22667
- wpa-supPLICANT: CVE-2023-52160
- xserver-xorg: CVE-2023-5574, CVE-2023-6816, CVE-2024-0229, CVE-2024-0408, CVE-2024-0409, CVE-2024-21885, CVE-2024-21886
- xwayland: CVE-2023-5367, CVE-2024-0408, CVE-2024-0409, CVE-2023-6816, CVE-2024-0229, CVE-2024-21885, CVE-2024-21886
- zlib: CVE-2023-45853 (ignored), CVE-2023-6992 (ignored)

### Recipe Upgrades in 5.0

- acl 2.3.1 -> 2.3.2
- acpica 20230628 -> 20240322
- alsa-lib 1.2.10 -> 1.2.11
- alsa-tools 1.2.5 -> 1.2.11
- alsa-ucm-conf 1.2.10 -> 1.2.11
- alsa-utils 1.2.10 -> 1.2.11
- appstream 0.16.3 -> 1.0.2

- autoconf 2.72c -> 2.72e
- bash 5.2.15 -> 5.2.21
- bash-completion 2.11 -> 2.12.0
- binutils 2.41 -> 2.42
- bluez5 5.69 -> 5.72
- boost 1.83.0 -> 1.84.0
- boost-build-native 1.83.0 -> 1.84.0
- btrfs-tools 6.5.1 -> 6.7.1
- cairo 1.16.0 -> 1.18.0
- cargo 1.70.0 -> 1.75.0
- cargo-c-native 0.9.18 -> 0.9.30+cargo-0.77.0
- ccache 4.8.3 -> 4.9.1
- cmake 3.27.7 -> 3.28.3
- cmake-native 3.27.7 -> 3.28.3
- createrepo-c 1.0.0 -> 1.0.4
- cronie 1.6.1 -> 1.7.1
- cross-localedef-native 2.38+git -> 2.39+git
- cups 2.4.6 -> 2.4.7
- curl 8.4.0 -> 8.7.1
- dbus-wait 0.1+git (6cc6077a36fe...) -> 0.1+git (64bc7c8fae61...)
- debianutils 5.13 -> 5.16
- desktop-file-utils 0.26 -> 0.27
- dhcpcd 10.0.2 -> 10.0.6
- diffoscope 249 -> 259
- diffstat 1.65 -> 1.66
- dnf 4.17.0 -> 4.19.0
- dos2unix 7.5.1 -> 7.5.2
- ed 1.19 -> 1.20.1
- efivar 38+39+git -> 39+39+git
- elfutils 0.189 -> 0.191
- ell 0.60 -> 0.63
- enchant2 2.6.2 -> 2.6.7

- epiphany 44.6 -> 46.0
- erofs-utils 1.6 -> 1.7.1
- ethtool 6.5 -> 6.7
- eudev 3.2.12 -> 3.2.14
- expat 2.5.0 -> 2.6.2
- ffmpeg 6.0 -> 6.1.1
- fontconfig 2.14.2 -> 2.15.0
- gawk 5.2.2 -> 5.3.0
- gcr 4.1.0 -> 4.2.0
- gdb 13.2 -> 14.2
- gettext 0.22 -> 0.22.5
- gettext-minimal-native 0.22 -> 0.22.5
- gi-docgen 2023.1 -> 2023.3
- git 2.42.0 -> 2.44.0
- glib-2.0 2.78.3 -> 2.78.4
- glib-networking 2.76.1 -> 2.78.1
- glibc 2.38+git -> 2.39+git
- glibc-locale 2.38 -> 2.39+git
- glibc-mtrace 2.38 -> 2.39+git
- glibc-scripts 2.38 -> 2.39+git
- glibc-testsuite 2.38+git -> 2.39+git
- glibc-y2038-tests 2.38+git -> 2.39+git
- glslang 1.3.261.1 -> 1.3.275.0
- gnu-config 20230216+git -> 20240101+git
- gnupg 2.4.3 -> 2.4.4
- gnutls 3.8.3 -> 3.8.4
- go 1.20.12 -> 1.22.2
- go-binary-native 1.20.12 -> 1.22.2
- go-native 1.20.12 -> 1.22.2
- go-runtime 1.20.12 -> 1.22.2
- gpgme 1.22.0 -> 1.23.2
- grub 2.06 -> 2.12

- grub-efi 2.06 -> 2.12
- gsettings-desktop-schemas 44.0 -> 46.0
- gst-devtools 1.22.9 -> 1.22.11
- gstreamer1.0 1.22.9 -> 1.22.11
- gstreamer1.0-libav 1.22.9 -> 1.22.11
- gstreamer1.0-omx 1.22.9 -> 1.22.11
- gstreamer1.0-plugins-bad 1.22.9 -> 1.22.11
- gstreamer1.0-plugins-base 1.22.9 -> 1.22.11
- gstreamer1.0-plugins-good 1.22.9 -> 1.22.11
- gstreamer1.0-plugins-ugly 1.22.9 -> 1.22.11
- gstreamer1.0-python 1.22.9 -> 1.22.11
- gstreamer1.0-rtsp-server 1.22.9 -> 1.22.11
- gstreamer1.0-vaapi 1.22.9 -> 1.22.11
- gtk+3 3.24.38 -> 3.24.41
- gtk4 4.12.3 -> 4.14.1
- harfbuzz 8.2.2 -> 8.3.0
- hwlatdetect 2.5 -> 2.6
- icu 73-2 -> 74-1
- inetutils 2.4 -> 2.5
- init-system-helpers 1.65.2 -> 1.66
- iproute2 6.5.0 -> 6.7.0
- iptables 1.8.9 -> 1.8.10
- iputils 20221126 -> 20240117
- iso-codes 4.15.0 -> 4.16.0
- iw 5.19 -> 6.7
- json-glib 1.6.6 -> 1.8.0
- kbd 2.6.3 -> 2.6.4
- kexec-tools 2.0.27 -> 2.0.28
- kmod 30 -> 31
- kmscube git -> 0.0.1+git
- libadwaita 1.4.2 -> 1.5.0
- libbsd 0.11.7 -> 0.12.1



- libcap-ng 0.8.3 -> 0.8.4
- libcap-ng-python 0.8.3 -> 0.8.4
- libcomps 0.1.19 -> 0.1.20
- libdnf 0.71.0 -> 0.73.0
- libdrm 2.4.116 -> 2.4.120
- libffi 3.4.4 -> 3.4.6
- libgit2 1.7.1 -> 1.7.2
- libgloss 4.3.0+git -> 4.4.0+git
- libgpg-error 1.47 -> 1.48
- libhandy 1.8.2 -> 1.8.3
- libical 3.0.16 -> 3.0.17
- libidn2 2.3.4 -> 2.3.7
- libinput 1.24.0 -> 1.25.0
- libksba 1.6.4 -> 1.6.6
- libmicrohttpd 0.9.77 -> 1.0.1
- libnl 3.8.0 -> 3.9.0
- libnotify 0.8.2 -> 0.8.3
- libpciaccess 0.17 -> 0.18
- libpcr2 10.42 -> 10.43
- libpng 1.6.40 -> 1.6.42
- libproxy 0.5.3 -> 0.5.4
- libpsl 0.21.2 -> 0.21.5
- librepo 1.16.0 -> 1.17.0
- librsvg 2.56.3 -> 2.57.1
- libsdl2 2.28.4 -> 2.30.0
- libseccomp 2.5.4 -> 2.5.5
- libsecret 0.21.1 -> 0.21.4
- libsolv 0.7.26 -> 0.7.28
- libsoup 3.4.2 -> 3.4.4
- libstd-rs 1.70.0 -> 1.75.0
- libtest-warnings-perl 0.031 -> 0.033
- libtirpc 1.3.3 -> 1.3.4

- libubootenv 0.3.4 -> 0.3.5
- libunistring 1.1 -> 1.2
- liburi-perl 5.21 -> 5.27
- libusb1 1.0.26 -> 1.0.27
- libuv 1.46.0 -> 1.48.0
- libva 2.19.0 -> 2.20.0
- libva-initial 2.19.0 -> 2.20.0
- libwpe 1.14.1 -> 1.14.2
- libxext 1.3.5 -> 1.3.6
- libxkbcommon 1.5.0 -> 1.6.0
- libxkbfile 1.1.2 -> 1.1.3
- libxml-parser-perl 2.46 -> 2.47
- libxml2 2.11.7 -> 2.12.5
- libxmlb 0.3.14 -> 0.3.15
- libxrandr 1.5.3 -> 1.5.4
- libxvmc 1.0.13 -> 1.0.14
- lighttpd 1.4.71 -> 1.4.74
- linux-firmware 20240220 -> 20240312
- linux-libc-headers 6.5 -> 6.6
- linux-yocto 6.1.78+git, 6.5.13+git -> 6.6.23+git
- linux-yocto-dev 6.6+git -> 6.9+git
- linux-yocto-rt 6.1.78+git, 6.5.13+git -> 6.6.23+git
- linux-yocto-tiny 6.1.78+git, 6.5.13+git -> 6.6.23+git
- llvm 17.0.3 -> 18.1.3
- lsof 4.98.0 -> 4.99.3
- ltp 20230516 -> 20240129
- lttnng-modules 2.13.10 -> 2.13.12
- lttnng-ust 2.13.6 -> 2.13.7
- lzip 1.23 -> 1.24
- makedepend 1.0.8 -> 1.0.9
- man-db 2.11.2 -> 2.12.0
- man-pages 6.05.01 -> 6.06

- mc 4.8.30 -> 4.8.31
- mesa 23.2.1 -> 24.0.2
- mesa-gl 23.2.1 -> 24.0.2
- meson 1.2.2 -> 1.3.1
- minicom 2.8 -> 2.9
- mmc-utils 0.1+git (613495ecaca9...) -> 0.1+git (b5ca140312d2...)
- mpg123 1.31.3 -> 1.32.5
- newlib 4.3.0+git -> 4.4.0+git
- nghttp2 1.57.0 -> 1.61.0
- numactl 2.0.16 -> 2.0.18
- ofono 2.1 -> 2.4
- opensbi 1.2 -> 1.4
- openssh 9.5p1 -> 9.6p1
- openssl 3.1.5 -> 3.2.1
- opkg 0.6.2 -> 0.6.3
- opkg-utils 0.6.2 -> 0.6.3
- orc 0.4.34 -> 0.4.38
- ovmf edk2-stable202308 -> edk2-stable202402
- p11-kit 0.25.0 -> 0.25.3
- pango 1.51.0 -> 1.52.0
- pciutils 3.10.0 -> 3.11.1
- piglit 1.0+gitr (71c21b1157c4...) -> 1.0+gitr (22eaf6a91cfd...)
- pkgconf 2.0.3 -> 2.1.1
- psplash 0.1+git (44afb7506d43...) -> 0.1+git (ecc191375669...)
- ptest-runner 2.4.2+git -> 2.4.3+git
- pulseaudio 16.1 -> 17.0
- puzzles 0.0+git (2d9e414ee316...) -> 0.0+git (80aac3104096...)
- python3 3.11.5 -> 3.12.3
- python3-alabaster 0.7.13 -> 0.7.16
- python3-attrs 23.1.0 -> 23.2.0
- python3-babel 2.12.1 -> 2.14.0
- python3-bcrypt 4.0.1 -> 4.1.2

- python3-beartype 0.15.0 -> 0.17.2
- python3-build 1.0.3 -> 1.1.1
- python3-certifi 2023.7.22 -> 2024.2.2
- python3-cffi 1.15.1 -> 1.16.0
- python3-cryptography 41.0.4 -> 42.0.5
- python3-cryptography-vectors 41.0.4 -> 42.0.5
- python3-cython 0.29.36 -> 3.0.8
- python3-dbusmock 0.29.1 -> 0.31.1
- python3-dtschema 2023.7 -> 2024.2
- python3-git 3.1.36 -> 3.1.42
- python3-gitdb 4.0.10 -> 4.0.11
- python3-hatch-fancy-pypi-readme 23.1.0 -> 24.1.0
- python3-hatch-vcs 0.3.0 -> 0.4.0
- python3-hatchling 1.18.0 -> 1.21.1
- python3-hypothesis 6.86.2 -> 6.98.15
- python3-idna 3.4 -> 3.6
- python3-importlib-metadata 6.8.0 -> 7.0.1
- python3-iso8601 2.0.0 -> 2.1.0
- python3-jsonschema 4.17.3 -> 4.21.1
- python3-license-expression 30.1.1 -> 30.2.0
- python3-lxml 4.9.3 -> 5.0.0
- python3-mako 1.2.4 -> 1.3.2
- python3-markdown 3.4.4 -> 3.5.2
- python3-markupsafe 2.1.3 -> 2.1.5
- python3-more-itertools 10.1.0 -> 10.2.0
- python3-numpy 1.26.0 -> 1.26.4
- python3-packaging 23.1 -> 23.2
- python3-pathspect 0.11.2 -> 0.12.1
- python3-pbr 5.11.1 -> 6.0.0
- python3-pip 23.2.1 -> 24.0
- python3-pluggy 1.3.0 -> 1.4.0
- python3-poetry-core 1.7.0 -> 1.9.0

- python3-psutil 5.9.5 -> 5.9.8
- python3-pyasn1 0.5.0 -> 0.5.1
- python3-pycairo 1.24.0 -> 1.26.0
- python3-pycryptodome 3.19.0 -> 3.20.0
- python3-pycryptodomex 3.19.0 -> 3.20.0
- python3-pygments 2.16.1 -> 2.17.2
- python3-pyopenssl 23.2.0 -> 24.0.0
- python3-pyrsistent 0.19.3 -> 0.20.0
- python3-pytest 7.4.2 -> 8.0.2
- python3-pytest-runner 6.0.0 -> 6.0.1
- python3-pytz 2023.3 -> 2024.1
- python3-ruamel-yaml 0.17.32 -> 0.18.6
- python3-scons 4.5.2 -> 4.6.0
- python3-setuptools 68.2.2 -> 69.1.1
- python3-setuptools-rust 1.7.0 -> 1.9.0
- python3-setuptools-scm 7.1.0 -> 8.0.4
- python3-spdx-tools 0.8.1 -> 0.8.2
- python3-sphinx-rtd-theme 1.3.0 -> 2.0.0
- python3-sphinxcontrib-applehelp 1.0.4 -> 1.0.8
- python3-sphinxcontrib-devhelp 1.0.2 -> 1.0.6
- python3-sphinxcontrib-htmlhelp 2.0.1 -> 2.0.5
- python3-sphinxcontrib-qthelp 1.0.3 -> 1.0.7
- python3-sphinxcontrib-serializinghtml 1.1.5 -> 1.1.10
- python3-subunit 1.4.2 -> 1.4.4
- python3-testtools 2.6.0 -> 2.7.1
- python3-trove-classifiers 2023.9.19 -> 2024.2.23
- python3-typing-extensions 4.8.0 -> 4.10.0
- python3-unittest-automake-output 0.1 -> 0.2
- python3-urllib3 2.0.7 -> 2.2.1
- python3-wcwidth 0.2.6 -> 0.2.13
- python3-wheel 0.41.2 -> 0.42.0
- qemu 8.1.4 -> 8.2.1

- qemu-native 8.1.4 -> 8.2.1
- qemu-system-native 8.1.4 -> 8.2.1
- repo 2.36.1 -> 2.42
- resolvconf 1.91 -> 1.92
- rpm 4.18.1 -> 4.19.1
- rt-tests 2.5 -> 2.6
- rust 1.70.0 -> 1.75.0
- rust-cross-canadian 1.70.0 -> 1.75.0
- rust-llvm 1.70.0 -> 1.75.0
- shaderc 2023.6 -> 2023.8
- shadow 4.13 -> 4.14.2
- shared-mime-info 2.2 -> 2.4
- socat 1.7.4.4 -> 1.8.0.0
- spirv-headers 1.3.261.1 -> 1.3.275.0
- spirv-tools 1.3.261.1 -> 1.3.275.0
- sqlite3 3.43.2 -> 3.45.1
- strace 6.5 -> 6.7
- stress-ng 0.16.05 -> 0.17.05
- subversion 1.14.2 -> 1.14.3
- swig 4.1.1 -> 4.2.1
- sysstat 12.7.4 -> 12.7.5
- systemd 254.4 -> 255.4
- systemd-boot 254.4 -> 255.4
- systemd-bootchart 234 -> 235
- systemtap 4.9 -> 5.0
- systemtap-native 4.9 -> 5.0
- taglib 1.13.1 -> 2.0
- ttyrun 2.29.0 -> 2.31.0
- u-boot 2023.10 -> 2024.01
- u-boot-tools 2023.10 -> 2024.01
- update-rc.d 0.8 (8636cf478d42...) -> 0.8 (b8f950105010...)
- usbutils 015 -> 017

- util-linux 2.39.2 -> 2.39.3
- util-linux-libuuid 2.39.2 -> 2.39.3
- vala 0.56.13 -> 0.56.15
- valgrind 3.21.0 -> 3.22.0
- vim 9.0.2190 -> 9.1.0114
- vim-tiny 9.0.2190 -> 9.1.0114
- virglrenderer 0.10.4 -> 1.0.1
- vte 0.72.2 -> 0.74.2
- vulkan-headers 1.3.261.1 -> 1.3.275.0
- vulkan-loader 1.3.261.1 -> 1.3.275.0
- vulkan-tools 1.3.261.1 -> 1.3.275.0
- vulkan-validation-layers 1.3.261.1 -> 1.3.275.0
- wayland-protocols 1.32 -> 1.33
- webkitgtk 2.40.5 -> 2.44.0
- weston 12.0.2 -> 13.0.0
- xkbcomp 1.4.6 -> 1.4.7
- xkeyboard-config 2.39 -> 2.41
- xprop 1.2.6 -> 1.2.7
- xwayland 23.2.4 -> 23.2.5
- xz 5.4.4 -> 5.4.6
- zlib 1.3 -> 1.3.1

## Contributors to 5.0

Thanks to the following people who contributed to this release:

- Adam Johnston
- Adithya Balakumar
- Adrian Freihofer
- Alassane Yattara
- Alejandro Hernandez Samaniego
- Aleksey Smirnov
- Alexander Kanavin
- Alexander Lussier-Cullen
- Alexander Sverdlin

- Alexandre Belloni
- Alexandre Truong
- Alex Bennée
- Alexis Lothoré
- Alex Kiernan
- Alex Stewart
- André Draszik
- Anibal Limon
- Anuj Mittal
- Archana Polampalli
- Arne Schwerdt
- Bartosz Golaszewski
- Baruch Siach
- Bastian Krause
- BELHADJ SALEM Talel
- BELOUARGA Mohamed
- Bruce Ashfield
- Changhyeok Bae
- Changqing Li
- Charlie Johnston
- Chen Qi
- Chi Xu
- Chris Laplante
- Christian Taedcke
- Christoph Vogtländer
- Claus Stovgaard
- Clay Chang
- Clément Péron
- Colin McAllister
- Corentin Guillevic
- Daniel Ammann
- david d zuhn



- David Reyna
- Deepthi Hemraj
- Denys Dmytriienko
- Derek Erdmann
- Desone Burns
- Dhairya Nagodra
- Dmitry Baryshkov
- Eero Aaltonen
- Eilís 'pidge' Ní Fhlannagáin
- Emil Kronborg
- Enguerrand de Ribaucourt
- Enrico Jörns
- Enrico Scholz
- Etienne Cordonnier
- Fabien Mahot
- Fabio Estevam
- Fahad Arslan
- Felix Moessbauer
- Florian Wickert
- Geoff Parker
- Glenn Strauss
- Harish Sadineni
- Hongxu Jia
- Ilya A. Kriveshko
- Jamin Lin
- Jan Vermaete
- Jason Andryuk
- Javier Tia
- Jeremy A. Puhlman
- Jérémy Rosen
- Jermain Horsman
- Jiang Kai

- Joakim Tjernlund
- Joao Marcos Costa
- Joe Slater
- Johan Bezem
- Johannes Schneider
- Jonathan GUILLOT
- Jon Mason
- Jörg Sommer
- Jose Quaresma
- Joshua Watt
- Julien Stephan
- Justin Bronder
- Kai Kang
- Kareem Zarka
- Kevin Hao
- Khem Raj
- Konrad Weihmann
- Lee Chee Yang
- Lei Maohui
- lixiaoyong
- Logan Gunthorpe
- Luca Ceresoli
- luca fancellu
- Lucas Stach
- Ludovic Jozeau
- Lukas Funke
- Maanya Goenka
- Malte Schmidt
- Marcel Ziswiler
- Marco Felsch
- Marcus Folkesson
- Marek Vasut

- Mark Asselstine
- Mark Hatle
- Markus Fuchs
- Markus Volk
- Marlon Rodriguez Garcia
- Marta Rybczynska
- Martin Hundebøll
- Martin Jansa
- Massimiliano Minella
- Maxin B. John
- Max Krummenacher
- Meenali Gupta
- Michael Halstead
- Michael Opdenacker
- Michal Sieron
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Munehisa Kamata
- Nick Owens
- Niko Mauno
- Ola x Nilsson
- Oleh Matushyn
- Patrick Williams
- Paul Barker
- Paul Eggleton
- Paul Gortmaker
- Pavel Zhukov
- Peter A. Bigot
- Peter Kjellerstedt
- Peter Marko
- Petr Vorel

- Philip Balister
- Philip Lorenz
- Philippe Rivest
- Piotr Łobacz
- Priyal Doshi
- Quentin Schulz
- Ragesh Nair
- Randolph Sapp
- Randy MacLeod
- Rasmus Villemoes
- Renat Khalikov
- Richard Haar
- Richard Purdie
- Robert Berger
- Robert Joslyn
- Robert P. J. Day
- Robert Yang
- Rodrigo M. Duarte
- Ross Burton
- Rouven Czerwinski
- Ryan Eatmon
- Sam Van Den Berge
- Saul Wold
- Sava Jakovljević
- Sean Nyekjaer
- Sergei Zhmylev
- Shinji Matsunaga
- Shubham Kulkarni
- Simone Weiß
- Siong W.LIM
- Soumya Sambu
- Sourav Kumar Pramanik

- Stefan Herbrechtsmeier
- Stéphane Veyret
- Steve Sakoman
- Sundeep KOKKONDA
- Thomas Perrot
- Thomas Wolber
- Timon Bergelt
- Tim Orling
- Timotheus Giuliani
- Tobias Hagelborn
- Tom Hochstein
- Tom Rini
- Toni Lammi
- Trevor Gamblin
- Trevor Woerner
- Ulrich Ölmann
- Valek Andrej
- venkata pyla
- Victor Kamensky
- Vijay Anusuri
- Vikas Katariya
- Vincent Davis Jr
- Viswanath Kraleti
- Vyacheslav Yurkov
- Wang Mingyu
- William A. Kennington III
- William Hauser
- William Lyu
- Xiangyu Chen
- Xiaotian Wu
- Yang Xu
- Yannick Rodriguez

- Yash Shinde
- Yi Zhao
- Yoann Congal
- Yogesh Tyagi
- Yogita Urade
- Zahir Hussain
- Zang Ruochen
- Zoltan Boszormenyi

## Repositories / Downloads for Yocto-5.0

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0](#)
- Git Revision: [fb91a49387cfb0c8d48303bb3354325ba2a05587](#)
- Release Artefact: [poky-fb91a49387cfb0c8d48303bb3354325ba2a05587](#)
- sha: [8a0dff4b677b9414ab814ed35d1880196123732ea16ab2fafa388bcc509b32ab](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0/poky-fb91a49387cfb0c8d48303bb3354325ba2a05587.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0/poky-fb91a49387cfb0c8d48303bb3354325ba2a05587.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0](#)
- Git Revision: [b65b4e5a8e4473d8ca43835ba17bc8bd4bdca277](#)
- Release Artefact: [oecore-b65b4e5a8e4473d8ca43835ba17bc8bd4bdca277](#)
- sha: [c7fd05d1a00c70acba2540e60dce01a1bdc4701ebff9a808784960240c69261d](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0/oecore-b65b4e5a8e4473d8ca43835ba17bc8bd4bdca277.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0/oecore-b65b4e5a8e4473d8ca43835ba17bc8bd4bdca277.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0](#)

- Git Revision: [acbba477893ef87388effc4679b7f40ee49fc852](#)
- Release Artefact: [meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852](#)
- sha: [3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-5.0/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0
- Git Revision: [c86466d51e8ff14e57a734c1eec5bb651fdc73ef](#)
- Release Artefact: [bitbake-c86466d51e8ff14e57a734c1eec5bb651fdc73ef](#)
- sha: [45c91294c1fa5a0044f1bb72a9bb69456bb458747114115af85c7664bf672d48](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0/bitbake-c86466d51e8ff14e57a734c1eec5bb651fdc73ef.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-5.0/bitbake-c86466d51e8ff14e57a734c1eec5bb651fdc73ef.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: yocto-5.0
- Git Revision: [0cdc0afd3332459d30cfc8f4c2e62bdcc23f5ed5](#)

### 17.7.3 Release notes for Yocto-5.0.1 (Scarthgap)

#### Security Fixes in Yocto-5.0.1

- N/A

#### Fixes in Yocto-5.0.1

- babeltrace2: upgrade 2.0.5 -> 2.0.6
- bind: upgrade 9.18.24 -> 9.18.25
- bitbake: cooker: Use hash client to ping upstream server
- build-appliance-image: Update to scarthgap head revision (b9b47b1a392b...)
- docs: add support for scarthgap 5.0 release
- docs: brief-yoctoprojectqs: explicit version dependency on websockets python module
- docs: brief-yoctoprojectqs: Update to the correct hash equivalence server address
- documentation/poky.yaml.in: drop mesa/sdl from essential host packages

- ell: upgrade 0.63 -> 0.64
- gcr: upgrade 4.2.0 -> 4.2.1
- icu: update 74-1 -> 74-2
- libdnf: upgrade 0.73.0 -> 0.73.1
- libsdl2: upgrade 2.30.0 -> 2.30.1
- libx11: upgrade 1.8.7 -> 1.8.9
- libxcursor: upgrade 1.2.1 -> 1.2.2
- libxml2: upgrade 2.12.5 -> 2.12.6
- local.conf.sample: Fix hashequivalence server address
- lttnng-tools: upgrade 2.13.11 -> 2.13.13
- manuals: standards.md: add standard for project names
- mesa: upgrade 24.0.2 -> 24.0.3
- migration-notes: add release notes for 4.0.18
- mpg123: upgrade 1.32.5 -> 1.32.6
- pango: upgrade 1.52.0 -> 1.52.1
- poky.conf: bump version for 5.0.1
- python3: skip test\_concurrent\_futures/test\_shutdown
- ref-manual: update releases.svg
- ref-manual: variables: add *USERADD\_DEPENDS*
- release-notes-5.0: update Repositories / Downloads section
- release-notes-5.0: update recipes changes
- release-notes-5.0: update new features
- rootfs-postcommands.bbclass: Only set DROPBEAR\_RSAKEY\_DIR once
- rpm: update 4.19.1 -> 4.19.1.1
- scripts/oe-setup-build: write a build environment initialization one-liner into the build directory
- sstate.bbclass: Add \_SSTATE\_EXCLUDEDEPS\_SYSROOT to vardepsexclude
- systemd: sed *ROOT\_HOME* only if sysusers *PACKAGECONFIG* is set

### Known Issues in Yocto-5.0.1

- N/A



## Contributors to Yocto-5.0.1

- Alexander Kanavin
- Christian Bräuner Sørensen
- Joshua Watt
- Lee Chee Yang
- Mark Hatle
- Michael Glembotzki
- Michael Halstead
- Michael Opdenacker
- Paul Eggleton
- Quentin Schulz
- Richard Purdie
- Steve Sakoman
- Trevor Gamblin
- Wang Mingyu

## Repositories / Downloads for Yocto-5.0.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.1`
- Git Revision: `4b07a5316ed4b858863dfdb7cab63859d46d1810`
- Release Artefact: `poky-4b07a5316ed4b858863dfdb7cab63859d46d1810`
- sha: `51d0c84da7dbcc8db04a674da39cfc73ea78aac22ee646ede5b6229937d4666a`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.1/poky-4b07a5316ed4b858863dfdb7cab63859d46d1810.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.1/poky-4b07a5316ed4b858863dfdb7cab63859d46d1810.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.1`
- Git Revision: `294a7dbe44f6b7c8d3a1de8c2cc182af37c4f916`
- Release Artefact: `oecore-294a7dbe44f6b7c8d3a1de8c2cc182af37c4f916`
- sha: `e9be51a3b1fe8a1f420483b912caf91bc429dcca303d462381876a643b73045e`

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.1/oecore-294a7dbe44f6b7c8d3a1de8c2cc182af37c4f916.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.1/oecore-294a7dbe44f6b7c8d3a1de8c2cc182af37c4f916.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: scarthgap
- Tag: yocto-5.0.1
- Git Revision: [acbba477893ef87388effc4679b7f40ee49fc852](https://git.yoctoproject.org/meta-mingw/commit/acbba477893ef87388effc4679b7f40ee49fc852)
- Release Artefact: meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852
- sha: 3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.1/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.1/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0.1
- Git Revision: [8f90d10f9efc9a32e13f6bd031992aece79fe7cc](https://git.openembedded.org/bitbake/commit/8f90d10f9efc9a32e13f6bd031992aece79fe7cc)
- Release Artefact: bitbake-8f90d10f9efc9a32e13f6bd031992aece79fe7cc
- sha: 519f02d5de7fbfac411532161d521123814dd9cc7d6b55488b5e7a547c1a6977
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.1/bitbake-8f90d10f9efc9a32e13f6bd031992aece79fe7cc.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.1/bitbake-8f90d10f9efc9a32e13f6bd031992aece79fe7cc.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: scarthgap
- Tag: yocto-5.0.1
- Git Revision: [875dfe69e93bf8fee3b8c07818a6ac059f228a13](https://git.yoctoproject.org/yocto-docs/commit/875dfe69e93bf8fee3b8c07818a6ac059f228a13)

## 17.7.4 Release notes for Yocto-5.0.2 (Scarthgap)

### Security Fixes in Yocto-5.0.2

- cups: Fix [CVE-2024-35235](#)
- gcc: Fix [CVE-2024-0151](#)
- gdk-pixbuf: Fix [CVE-2022-48622](#)

- ghostscript: fix [CVE-2024-29510](#), [CVE-2024-33869](#), [CVE-2024-33870](#) and [CVE-2024-33871](#)
- git: Fix [CVE-2024-32002](#), [CVE-2024-32004](#), [CVE-2024-32020](#), [CVE-2024-32021](#) and [CVE-2024-32465](#)
- glib-2.0: Fix [CVE-2024-34397](#)
- glibc: Fix [CVE-2024-2961](#), [CVE-2024-33599](#), [CVE-2024-33600](#), [CVE-2024-33601](#) and [CVE-2024-33602](#)
- ncurses: Fix [CVE-2023-45918](#) and [CVE-2023-50495](#)
- openssl: Fix [CVE-2024-4603](#) and [CVE-2024-4741](#)
- util-linux: Fix [CVE-2024-28085](#)
- xserver-xorg: Fix [CVE-2024-31080](#), [CVE-2024-31081](#), [CVE-2024-31082](#) and [CVE-2024-31083](#)

### Fixes in Yocto-5.0.2

- appstream: Upgrade to 1.0.3
- apr: submit 0001-Add-option-to-disable-timed-dependant-tests.patch upstream
- base-files: profile: fix error sh: 1: unknown operand
- bash: Fix file-substitution error-handling bug
- bash: mark build-tests.patch as Inappropriate
- binutils: Fix aarch64 disassembly abort
- bitbake: bb: Use namedtuple for Task data
- bitbake: cooker: Handle ImportError for websockets
- bitbake: fetch2/gcp: Add missing runfetchcmd import
- bitbake: fetch2/wget: Canonicalize *DL\_DIR* paths for wget2 compatibility
- bitbake: fetch2/wget: Fix failure path for files that are empty or don't exist
- bitbake: hashserv: client: Add batch stream API
- bitbake: parse: Improve/fix cache invalidation via mtime
- bitbake: runqueue: Add timing warnings around slow loops
- bitbake: runqueue: Allow rehash loop to exit in case of interrupts
- bitbake: runqueue: Improve rehash get\_unihash parallelism
- bitbake: runqueue: Process unihashes in parallel at init
- bitbake: siggen/runqueue: Report which dependencies affect the taskhash
- bitbake: siggen: Enable batching of unihash queries
- bitbake: tests/fetch: Tweak test to match upstream repo url change
- bitbake: tests/fetch: Tweak to work on Fedora40
- build-appliance-image: Update to scarthgap head revision
- busybox: update [CVE-2022-28391](#) patches upstream status

- cdrtools-native: Fix build with GCC 14
- classes: image\_types: apply EXTRA\_IMAGECMD:squashfs\* in oe\_mksquashfs()
- classes: image\_types: quote variable assignment needed by dash
- consolekit: Disable incompatible-pointer-types warning as error
- cracklib: Modify patch to compile with GCC 14
- cronie: Upgrade to 1.7.2
- cups: Upgrade to 2.4.9
- db: ignore implicit-int and implicit-function-declaration issues fatal with gcc-14
- devtool: modify: Catch git submodule error for go code
- devtool: standard: update-recipe/finish: fix update localfile in another layer
- devtool: sync: Fix Execution error
- expect: ignore various issues now fatal with gcc-14
- expect: mark patches as Inactive-Upstream
- gawk: fix readline detection
- gcc : Upgrade to v13.3
- gcc-runtime: libgomp fix for gcc 14 warnings with mandb selftest
- gdk-pixbuf: Upgrade to 2.42.12
- git: set --with-gitconfig=/etc/gitconfig for -native builds
- git: Upgrade to 2.44.1
- glib-2.0: Upgrade to 2.78.6
- glibc: Update to latest on stable 2.39 branch (273a835fe7...)
- glibc: correct *LICENSE* to "GPL-2.0-only & LGPL-2.1-or-later"
- go: Drop the linkmode completely
- goarch: Revert "disable dynamic linking globally"
- gstreamer1.0-plugins-good: Include qttools-native during the build with qt5 *PACKAGECONFIG*
- gtk4: Disable int-conversion warning as error
- icu: add upstream submission links for fix-install-manx.patch
- ipk: Fix clean up of extracted IPK payload
- iproute2: Fix build with GCC-14
- iproute2: drop obsolete patch
- iputils: splitting the ping6 as a package
- kea: Remove -fvisibility-inlines-hidden from C++ flags

- kea: remove unnecessary reproducibility patch
- kernel.bbclass: check, if directory exists before removing empty module directory
- kexec-tools: Fix build with GCC-14 on musl
- lib/oe/package-manager: allow including self in create\_packages\_dir
- lib/package\_manager/ipk: Do not hardcode payload compression algorithm
- libarchive: Upgrade to 3.7.4
- libcgroup: fix build on non-systemd systems
- libgloss: Do not apply non-existent patch
- libinput: fix building with debug-gui option
- libtraceevent: submit meson.patch upstream
- libunwind: ignore various issues now fatal with gcc-14
- libusb1: Set *CVE\_PRODUCT*
- llvm: Switch to using release tarballs
- llvm: Upgrade to 18.1.5
- lrzsz connman-gnome libfm: ignore various issues fatal with gcc-14
- ltp: Fix build with GCC-14
- ltp: add iputils-ping6 to *RDEPENDS*
- ltng-ust: Upgrade to 2.13.8
- mesa: Upgrade to 24.0.5
- oeqa/postactions: Do not use -l option with df
- oeqa/sdk/assimp: Upgrade and fix for gcc 14
- oeqa/sdkext/devtool: replace use of librdfa
- oeqa/selftest/debuginfod: use localpkgfeed to speed server startup
- oeqa/selftest/devtool: Revert fix test\_devtool\_add\_git\_style2"
- oeqa/selftest/devtool: add test for modifying recipes using go.bbclass
- oeqa/selftest/devtool: add test for updating local files into another layer
- oeqa/selftest/devtool: fix \_test\_devtool\_add\_git\_url
- oeqa: selftest: context: run tests serially if testtools/subunit modules are not found
- openssl: Upgrade to 3.2.2
- p11-kit: ignore various issues fatal with gcc-14 (for 32bit MACHINES)
- patchtest: test\_metadata: fix invalid escape sequences
- poky.conf: bump version for 5.0.2

- ppp: Add RSA-MD in *LICENSE*
- procps: fix build with new glibc but old kernel headers
- ptest-runner: Bump to 2.4.4 (95f528c)
- recipetool: Handle several go-import tags in go resolver
- recipetool: Handle unclean response in go resolver
- run-postinsts.service: Removed --no-reload to fix reload warning when users execute systemctl in the first boot.
- selftest/classes: add localpkgfeed class
- serf: mark patch as inappropriate for upstream submission
- taglib: Upgrade to 2.0.1
- ttyrun: define *CVE\_PRODUCT*
- uboot-sign: fix loop in do\_uboot\_assemble\_fitimage
- update-rc.d: add +git to *PV*
- webkitgtk: Upgrade to 2.44.1
- xinput-calibrator: mark upstream as inactive in a patch
- xserver-xorg: Upgrade to 21.1.12
- yocto-uninative: Update to 4.5 for gcc 14
- zip: Fix build with gcc-14

### Known Issues in Yocto-5.0.2

- N/A

### Contributors to Yocto-5.0.2

- Adriaan Schmidt
- Alexander Kanavin
- Alexandre Truong
- Anton Almqvist
- Archana Polampalli
- Changqing Li
- Deepthi Hemraj
- Felix Nilsson
- Heiko Thole
- Jose Quaresma
- Joshua Watt
- Julien Stephan

- Kai Kang
- Khem Raj
- Lei Maohui
- Marc Ferland
- Marek Vasut
- Mark Hatle
- Martin Hundebøll
- Martin Jansa
- Maxin B. John
- Michael Halstead
- Mingli Yu
- Ola x Nilsson
- Peter Marko
- Philip Lorenz
- Poonam Jadhav
- Ralph Siemsen
- Rasmus Villemoes
- Ricardo Simoes
- Richard Purdie
- Robert Joslyn
- Ross Burton
- Rudolf J Streif
- Siddharth Doshi
- Soumya Sambu
- Steve Sakoman
- Sven Schwermer
- Trevor Gamblin
- Vincent Kriek
- Wang Mingyu
- Xiangyu Chen
- Yogita Urade
- Zev Weiss

- Zoltan Boszormenyi

## Repositories / Downloads for Yocto-5.0.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.2`
- Git Revision: `f7def85be9f99dcb4ba488bead201f670304379b`
- Release Artefact: `poky-f7def85be9f99dcb4ba488bead201f670304379b`
- sha: `0610a3175846d87f8a853020e8d517c94fe5e8b3fd4e40cd2d0ddbc22e75db4c`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.2/poky-f7def85be9f99dcb4ba488bead201f670304379b.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.2/poky-f7def85be9f99dcb4ba488bead201f670304379b.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.2`
- Git Revision: `803cc32e72b4fc2fc28d92090e61f5dd288a10cb`
- Release Artefact: `oecore-803cc32e72b4fc2fc28d92090e61f5dd288a10cb`
- sha: `b63f1214438e540ec15f1ec7f49615f31584c93e9cff10833273eefc710a7862`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.2/oecore-803cc32e72b4fc2fc28d92090e61f5dd288a10cb.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.2/oecore-803cc32e72b4fc2fc28d92090e61f5dd288a10cb.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.2`
- Git Revision: `acbba477893ef87388effc4679b7f40ee49fc852`
- Release Artefact: `meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852`
- sha: `3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.2/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.2/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>



- Branch: 2.8
- Tag: yocto-5.0.2
- Git Revision: 8714a02e13477a9d97858b3642e05f28247454b5
- Release Artefact: bitbake-8714a02e13477a9d97858b3642e05f28247454b5
- sha: f22b56447e321c308353196da1d6dd76af5e9957e7e654c75dfd707f58091fd1
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.2/bitbake-8714a02e13477a9d97858b3642e05f28247454b5.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.2/bitbake-8714a02e13477a9d97858b3642e05f28247454b5.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: scarthgap
- Tag: yocto-5.0.2
- Git Revision: 875dfe69e93bf8fee3b8c07818a6ac059f228a13

## 17.7.5 Release notes for Yocto-5.0.3 (Scarthgap)

### Security Fixes in Yocto-5.0.3

- bind: Fix CVE-2024-0760, CVE-2024-1737, CVE-2024-1975 and CVE-2024-4076
- busybox: Fix CVE-2023-42366, CVE-2023-42364, CVE-2023-42365, CVE-2021-42380 and CVE-2023-42363
- cpio: Ignore CVE-2023-7216
- curl: Fix CVE-2024-6197
- ffmpeg: Fix CVE-2023-49502, CVE-2024-31578 and CVE-2024-31582
- ghostscript: Fix CVE-2023-52722
- go: Fix CVE-2024-24790
- gstreamer1.0-plugins-base: Fix CVE-2024-4453
- less: Fix CVE-2024-32487
- libxml2: Fix CVE-2024-34459
- libyaml: Ignore CVE-2024-35328
- linux-yocto/6.6: Fix CVE-2024-23307, CVE-2024-24861, CVE-2024-26642, CVE-2024-26643, CVE-2024-26654, CVE-2024-26656 and CVE-2023-47233
- linux-yocto/6.6: Ignore CVE-2019-25160, CVE-2019-25162, CVE-2020-36775, CVE-2020-36776, CVE-2020-36777, CVE-2020-36778, CVE-2020-36779, CVE-2020-36780, CVE-2020-36781, CVE-2020-36782, CVE-2020-36783, CVE-2020-36784, CVE-2020-36785, CVE-2020-36786, CVE-2020-36787,

1330 Capitolo 17. Informazioni sulla Release

CVE-2021-47161, CVE-2021-47162, CVE-2021-47163, CVE-2021-47164, CVE-2021-47165, CVE-2021-47166, CVE-2021-47167, CVE-2021-47168, CVE-2021-47169, CVE-2021-47170, CVE-2021-47171, CVE-2021-47172, CVE-2021-47173, CVE-2021-47174, CVE-2021-47175, CVE-2021-47176, CVE-2021-47177, CVE-2021-47178, CVE-2021-47179, CVE-2021-47180, CVE-2022-48626, CVE-2022-48627, CVE-2022-48628, CVE-2022-48629 and CVE-2022-48630

- **linux-yocto/6.6 (cont.): Ignore** CVE-2023-6270, CVE-2023-6356, CVE-2023-6536, CVE-2023-7042, CVE-2023-28746, CVE-2023-52465, CVE-2023-52467, CVE-2023-52468, CVE-2023-52469, CVE-2023-52470, CVE-2023-52471, CVE-2023-52472, CVE-2023-52473, CVE-2023-52474, CVE-2023-52475, CVE-2023-52476, CVE-2023-52477, CVE-2023-52478, CVE-2023-52479, CVE-2023-52480, CVE-2023-52481, CVE-2023-52482, CVE-2023-52483, CVE-2023-52484, CVE-2023-52486, CVE-2023-52487, CVE-2023-52488, CVE-2023-52489, CVE-2023-52490, CVE-2023-52491, CVE-2023-52492, CVE-2023-52493, CVE-2023-52494, CVE-2023-52495, CVE-2023-52497, CVE-2023-52498, CVE-2023-52499, CVE-2023-52500, CVE-2023-52501, CVE-2023-52502, CVE-2023-52503, CVE-2023-52504, CVE-2023-52505, CVE-2023-52506, CVE-2023-52507, CVE-2023-52508, CVE-2023-52509, CVE-2023-52510, CVE-2023-52511, CVE-2023-52512, CVE-2023-52513, CVE-2023-52515, CVE-2023-52516, CVE-2023-52517, CVE-2023-52518, CVE-2023-52519, CVE-2023-52520, CVE-2023-52522, CVE-2023-52523, CVE-2023-52524, CVE-2023-52525, CVE-2023-52526, CVE-2023-52527, CVE-2023-52528, CVE-2023-52529, CVE-2023-52530, CVE-2023-52531, CVE-2023-52532, CVE-2023-52559, CVE-2023-52560, CVE-2023-52561, CVE-2023-52562, CVE-2023-52563, CVE-2023-52564, CVE-2023-52565, CVE-2023-52566, CVE-2023-52567, CVE-2023-52568, CVE-2023-52569, CVE-2023-52570, CVE-2023-52571, CVE-2023-52572, CVE-2023-52573, CVE-2023-52574, CVE-2023-52575, CVE-2023-52576, CVE-2023-52577, CVE-2023-52578, CVE-2023-52580, CVE-2023-52581, CVE-2023-52582, CVE-2023-52583, CVE-2023-52584, CVE-2023-52587, CVE-2023-52588, CVE-2023-52589, CVE-2023-52591, CVE-2023-52593, CVE-2023-52594, CVE-2023-52595, CVE-2023-52596, CVE-2023-52597, CVE-2023-52598, CVE-2023-52599, CVE-2023-52600, CVE-2023-52601, CVE-2023-52602, CVE-2023-52603, CVE-2023-52604, CVE-2023-52606, CVE-2023-52607, CVE-2023-52608, CVE-2023-52609, CVE-2023-52610, CVE-2023-52611, CVE-2023-52612, CVE-2023-52613, CVE-2023-52614, CVE-2023-52615, CVE-2023-52616, CVE-2023-52617, CVE-2023-52618, CVE-2023-52619, CVE-2023-52620, CVE-2023-52621, CVE-2023-52622, CVE-2023-52623, CVE-2023-52626, CVE-2023-52627, CVE-2023-52628, CVE-2023-52629, CVE-2023-52630, CVE-2023-52631, CVE-2023-52632, CVE-2023-52633, CVE-2023-52635, CVE-2023-52636, CVE-2023-52637, CVE-2023-52638, CVE-2023-52639, CVE-2023-52640, CVE-2023-52641, CVE-2024-0841, CVE-2024-22099, CVE-2024-23196, CVE-2024-26600, CVE-2024-26601, CVE-2024-26602, CVE-2024-26603, CVE-2024-26604, CVE-2024-26605, CVE-2024-26606, CVE-2024-26607, CVE-2024-26608, CVE-2024-26610, CVE-2024-26611, CVE-2024-26612, CVE-2024-26614, CVE-2024-26615, CVE-2024-26616, CVE-2024-26617, CVE-2024-26618, CVE-2024-26619, CVE-2024-26620, CVE-2024-26621, CVE-2024-26622, CVE-2024-26623, CVE-2024-26625, CVE-2024-26626, CVE-2024-26627, CVE-2024-26629, CVE-2024-26630, CVE-2024-26631, CVE-2024-26632, CVE-2024-26633, CVE-2024-26634, CVE-2024-26635, CVE-2024-26636, CVE-2024-26637, CVE-2024-26638, CVE-2024-26639, CVE-2024-26640, CVE-2024-26641, CVE-2024-26644, CVE-2024-26645, CVE-2024-26646, CVE-2024-26647, CVE-2024-26648, CVE-2024-26649, CVE-2024-26650, CVE-2024-26651, CVE-2024-26652, CVE-2024-26653, CVE-2024-26657, CVE-2024-26659, CVE-2024-26660, CVE-2024-26661, CVE-2024-26662, CVE-2024-26663, CVE-2024-26664, CVE-2024-26665, CVE-2024-26666, CVE-2024-26667, CVE-2024-26668, CVE-2024-26669, CVE-2024-26670, CVE-2024-26671, CVE-2024-26673, CVE-2024-26674, CVE-2024-26675, CVE-2024-26676, CVE-2024-26677, CVE-2024-26678,

CVE-2024-26679, CVE-2024-26680, CVE-2024-26681, CVE-2024-26682, CVE-2024-26683, CVE-2024-26684, CVE-2024-26685, CVE-2024-26687, CVE-2024-26688, CVE-2024-26689, CVE-2024-26690, CVE-2024-26691, CVE-2024-26692, CVE-2024-26693, CVE-2024-26694, CVE-2024-26695, CVE-2024-26696, CVE-2024-26697, CVE-2024-26698, CVE-2024-26700, CVE-2024-26702, CVE-2024-26703, CVE-2024-26704, CVE-2024-26705, CVE-2024-26706, CVE-2024-26707, CVE-2024-26708, CVE-2024-26709, CVE-2024-26710, CVE-2024-26711, CVE-2024-26712, CVE-2024-26713, CVE-2024-26714, CVE-2024-26715, CVE-2024-26716, CVE-2024-26717, CVE-2024-26718, CVE-2024-26719, CVE-2024-26720, CVE-2024-26721, CVE-2024-26722, CVE-2024-26723, CVE-2024-26724, CVE-2024-26725, CVE-2024-26726, CVE-2024-26727, CVE-2024-26728, CVE-2024-26729, CVE-2024-26730, CVE-2024-26731, CVE-2024-26732, CVE-2024-26733, CVE-2024-26734, CVE-2024-26735, CVE-2024-26736, CVE-2024-26737, CVE-2024-26738, CVE-2024-26739, CVE-2024-26740, CVE-2024-26741, CVE-2024-26742, CVE-2024-26743, CVE-2024-26744, CVE-2024-26745, CVE-2024-26746, CVE-2024-26747, CVE-2024-26748, CVE-2024-26749, CVE-2024-26750, CVE-2024-26751, CVE-2024-26752, CVE-2024-26753, CVE-2024-26754, CVE-2024-26755, CVE-2024-26759, CVE-2024-26760, CVE-2024-26761, CVE-2024-26762, CVE-2024-26763, CVE-2024-26764, CVE-2024-26765, CVE-2024-26766, CVE-2024-26767, CVE-2024-26768, CVE-2024-26769, CVE-2024-26770, CVE-2024-26771, CVE-2024-26772, CVE-2024-26773, CVE-2024-26774, CVE-2024-26775, CVE-2024-26776, CVE-2024-26777, CVE-2024-26778, CVE-2024-26779, CVE-2024-26780, CVE-2024-26781, CVE-2024-26782, CVE-2024-26783, CVE-2024-26786, CVE-2024-26787, CVE-2024-26788, CVE-2024-26789, CVE-2024-26790, CVE-2024-26791, CVE-2024-26792, CVE-2024-26793, CVE-2024-26794, CVE-2024-26795, CVE-2024-26796, CVE-2024-26798, CVE-2024-26799, CVE-2024-26800, CVE-2024-26801, CVE-2024-26802, CVE-2024-26803, CVE-2024-26804, CVE-2024-26805, CVE-2024-26807, CVE-2024-26808 and CVE-2024-26809

- llvm: Fix CVE-2024-0151
- ofono: Fix CVE-2023-2794
- openssh: Fix CVE-2024-6387 and CVE-2024-39894
- openssl: Fix CVE-2024-5535
- pam: Fix CVE-2024-22365
- python3-idna: Fix CVE-2024-3651
- qemu: Fix CVE-2023-6683, CVE-2024-3446, CVE-2024-3447, CVE-2024-3567, CVE-2024-26327 and CVE-2024-26328
- ruby: Fix CVE-2023-36617 and CVE-2024-27281
- vite: Fix CVE-2024-37535
- wget: Fix for CVE-2024-38428

### **Fixes in Yocto-5.0.3**

- apt-native: don't let dpkg overwrite files by default
- archiver.bbclass: Fix work-shared checking for kernel recipes
- automake: mark new\_rt\_path\_for\_test-driver.patch as Inappropriate
- bash: fix configure checks that fail with GCC 14.1

- bind: upgrade to 9.18.28
- binutils: stable 2.42 branch updates
- bitbake: codeparser/data: Ensure module function contents changing is accounted for
- bitbake: codeparser: Skip non-local functions for module dependencies
- build-appliance-image: Update to scarthgap head revision
- cargo: remove True option to getVar calls
- classes/create-spdx-2.2: Fix *SPDX* Namespace Prefix
- classes/kernel: No symlink in postinst without KERNEL\_IMAGETYPE\_SYMLINK
- cmake-qemu.bbclass: fix if criterion
- create-spdx-3.0/populate\_sdk\_base: Add SDK\_CLASSES inherit mechanism to fix tarball *SPDX* manifests
- create-spdx-*'\*'*: Support multilibs via SPDX\_MULTILIB\_SSTATE\_ARCHS
- curl: correct the *PACKAGECONFIG* for native/nativesdk
- curl: locale-base-en-us isn't glibc-specific
- curl: skip FTP tests in run-ptest
- cve-check: Introduce CVE\_CHECK\_MANIFEST\_JSON\_SUFFIX
- cve-exclusion: Drop the version comparison/warning
- devtool: ide-sdk: correct help typo
- dnf: Fix missing leading whitespace with ':append'
- dpkg: mark patches adding custom non-debian architectures as inappropriate for upstream
- ed: upgrade to 1.20.2
- expect: fix configure with GCC 14
- ffmpeg: backport patch to fix errors with GCC 14
- ffmpeg: backport patches to use new Vulkan AV1 codec API
- flac: fix buildpaths warnings
- fribidi: upgrade to 1.0.14
- gawk: Remove References to /usr/local/bin/gawk
- gawk: update patch status
- gettext: fix a parallel build issue
- ghostscript: upgrade to 10.03.1
- glib-networking: submit eagain.patch upstream
- glibc: cleanup old cve status
- glibc: stable 2.39 branch updates

- glslang: mark 0001-generate-glslang-pkg-config.patch as Inappropriate
- go: drop the old 1.4 bootstrap C version
- go: upgrade to 1.22.5
- gpgme: move gpgme-tool to own sub-package
- grub,grub-efi: Remove -mfpmath=sse on x86
- grub: mark grub-module-explicitly-keeps-symbolic-module\_license.patch as a workaround
- gstreamer1.0: skip another known flaky test
- gstreamer: upgrade to 1.22.12
- insane.bbclass: fix *HOST\_* variable names
- insane.bbclass: remove leftover variables and comment
- insane.bbclass: remove skipping of cross-compiled packages
- insane: handle dangling symlinks in the libdir QA check
- iptables: fix memory corruption when parsing nft rules
- iptables: fix save/restore symlinks with libnftnl *PACKAGECONFIG* enabled
- iptables: submit 0001-configure-Add-option-to-enable-disable-libnftnl.patch upstream
- kexec-tools: submit 0003-kexec-ARM-Fix-add\_buffer\_phys\_virt-align-issue.patch upstream
- layer.conf: Add os-release to *SIGGEN\_EXCLUDERECIPES\_ABISAFE*
- libacpi: mark patches as inactive-upstream
- libadwaita: upgrade to 1.5.1
- libcap-ng-python: upgrade to 0.8.5
- libcap-ng: upgrade to 0.8.5
- libmnl: explicitly disable doxygen
- libnl: change *HOMEPAGE*
- libpam: fix runtime error in pam\_pwhistory module
- libpng: update *SRC\_URI*
- libportal: fix rare build race
- libstd-rs: set *CVE\_PRODUCT* to rust
- libxcrypt: correct the check for a working libucontext.h
- libxml2: upgrade to 2.12.8
- linux-yocto-custom: Fix comment override syntax
- linux-yocto/6.6: cfg: drop obsolete options
- linux-yocto/6.6: cfg: introduce Intel NPU fragment

- linux-yocto/6.6: fix AMD boot trace
- linux-yocto/6.6: fix kselftest failures
- linux-yocto/6.6: intel configuration changes
- linux-yocto/6.6: nft: enable veth
- linux-yocto/6.6: update to v6.6.35
- linux-yocto: Enable team net driver
- linuxloader: add -armhf on arm only for *TARGET\_FPU* 'hard'
- llvm: upgrade to 18.1.6
- maintainers.inc: update self e-mail address
- maintainers: Drop go-native as recipe removed
- mesa: Fix missing leading whitespace with ':append'
- mesa: remove obsolete 0001-meson.build-check-for-all-linux-host\_os-combinations.patch
- mesa: upgrade to 24.0.7
- meson: don't use deprecated pkgconfig variable
- migration-guides: add release notes for 4.0.19
- migration-guides: add release notes for 5.0.2
- migration-notes: add release notes for 5.0.1
- mmc-utils: fix URL
- mobile-broadband-provider-info: upgrade to 20240407
- multilib.bbclass: replace deprecated e.data with d
- multilib.conf: remove appending to *PKG\_CONFIG\_PATH*
- nasm: upgrade to 2.16.03
- ncurses: switch to new mirror
- oeqa/runtime/scp: requires openssh-sftp-server
- oeqa/runtime: fix race-condition in minidebuginfo test
- oeqa/runtime: fix regression in minidebuginfo test
- oeqa/runtime: make minidebuginfo test work with coreutils
- oeqa/sdk/case: Ensure *DL\_DIR* is populated with artefacts if used
- oeqa/sdk/case: Skip SDK test cases when *TCLIBC* is newlib
- oeqa/selftest/devtool: Fix for usrmerge in *DISTRO\_FEATURES*
- oeqa/selftest/recipe tool: Fix for usrmerge in *DISTRO\_FEATURES*
- openssh: drop rejected patch fixed in 8.6p1 release

- openssl: systemd notification was implemented upstream
- openssl: systemd sd-notify patch was rejected upstream
- orc: upgrade to 0.4.39
- package.py: Fix static debuginfo split
- package.py: Fix static library processing
- pcmanfm: Disable incompatible-pointer-types warning as error
- perl: submit the rest of determinism.patch upstream
- pixman: fixing inline failure with -Og
- poky.conf: bump version for 5.0.3
- populate\_sdk\_ext.bbclass: Fix undefined variable error
- pseudo: Fix to work with glibc 2.40
- pseudo: Update to include open symlink handling bugfix
- pseudo: Update to pull in python 3.12+ fix
- python3-attrs: drop python3-ctypes from *RDEPENDS*
- python3-bcrypt: drop python3-six from *RDEPENDS*
- python3-idna: upgrade to 3.7
- python3-jinja2: upgrade to 3.1.4
- python3-pyopenssl: drop python3-six from *RDEPENDS*
- python3-requests: cleanup *RDEPENDS*
- python3-setuptools: drop python3-2to3 from *RDEPENDS*
- python3: Treat UID/GID overflow as failure
- python3: skip test\_concurrent\_futures/test\_deadlock
- python3: skip test\_multiprocessing/test\_active\_children test
- python3: submit deterministic\_imports.patch upstream as a ticket
- python3: upgrade to 3.12.4
- qemu: upgrade to 8.2.3
- rng-tools: ignore incompatible-pointer-types errors for now
- rt-tests: rt\_bmark.py: fix TypeError
- rust-cross-canadian: set *CVE\_PRODUCT* to rust
- rust: Add new variable RUST\_ENABLE\_EXTRA\_TOOLS
- sanity: Check if tar is gnutar
- sdk: Fix path length limit to match reserved size



- selftest-hardlink: Add additional test cases
- selftest/cases/runtime\_test: Exclude centos-9 from virgl tests
- selftest: add Upstream-Status to .patch files
- settings-daemon: submit addsoundkeys.patch upstream and update to a revision that has it
- systemd.bbclass: Clarify error message
- tcp-wrappers: mark all patches as inactive-upstream
- tzdata: Add tzdata.zi to tzdata-core package
- vorbis: mark patch as Inactive-Upstream
- vulkan-samples: fix do\_compile error when -Og enabled
- watchdog: Set watchdog\_module in default config
- webkitgtk: fix do\_compile errors on beaglebone-yocto
- webkitgtk: fix do\_configure error on beaglebone-yocto
- weston: upgrade to 13.0.1
- wic/partition.py: Set hash\_seed for empty ext partition
- wic: bootimg-efi: fix error handling
- wic: engine.py: use raw string for escape sequence
- wireless-regdb: upgrade to 2024.05.08
- xserver-xorg: upgrade to 21.1.13
- xz: Update *LICENSE* variable for xz packages

### Known Issues in Yocto-5.0.3

- N/A

### Contributors to Yocto-5.0.3

- Adithya Balakumar
- Aleksandar Nikolic
- Alexander Kanavin
- Antonin Godard
- Archana Polampalli
- Ashish Sharma
- Benjamin Szőke
- Bruce Ashfield
- Changqing Li
- Chen Qi

- Christian Taedcke
- Deepthi Hemraj
- Denys Dmytriienko
- Dmitry Baryshkov
- Emil Kronborg
- Enrico Jörns
- Etienne Cordonnier
- Guðni Már Gilbert
- Hitendra Prajapati
- Jonas Gorski
- Jookia
- Jose Quaresma
- Joshua Watt
- Jörg Sommer
- Kai Kang
- Khem Raj
- Kirill Yatsenko
- Lee Chee Yang
- Mark Hatle
- Markus Volk
- Martin Jansa
- Michael Opdenacker
- Mingli Yu
- Niko Mauno
- Patrick Wicki
- Peter Marko
- Quentin Schulz
- Ranjitsinh Rathod
- Richard Purdie
- Robert Kovacsics
- Ross Burton
- Siddharth Doshi

- Simone Weiß
- Soumya Sambu
- Steve Sakoman
- Sundeep KOKKONDA
- Trevor Gamblin
- Vijay Anusuri
- Wadim Egorov
- Wang Mingyu
- Xiangyu Chen
- Yi Zhao
- Yogita Urade
- Zahir Hussain

## Repositories / Downloads for Yocto-5.0.3

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.3`
- Git Revision: `0b37512fb4b231cc106768e2a7328431009b3b70`
- Release Artefact: `poky-0b37512fb4b231cc106768e2a7328431009b3b70`
- sha: `b37fe0b2f6a685ee94b4af55f896cbf52ba69023e10eb21d3e54798ca21ace79`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.3/poky-0b37512fb4b231cc106768e2a7328431009b3b70.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.3/poky-0b37512fb4b231cc106768e2a7328431009b3b70.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.3`
- Git Revision: `236ac1b43308df722a78d3aa20aef065dfae5b2b`
- Release Artefact: `oecore-236ac1b43308df722a78d3aa20aef065dfae5b2b`
- sha: `44b89feba9563c2281c8c2f45037dd7c312fb20e8b7d9289b25f0ea0fe1fc2c4`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.3/oecore-236ac1b43308df722a78d3aa20aef065dfae5b2b.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.3/oecore-236ac1b43308df722a78d3aa20aef065dfae5b2b.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.3`
- Git Revision: `acbba477893ef87388effc4679b7f40ee49fc852`
- Release Artefact: `meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852`
- sha: `3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.3/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.3/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.8`
- Tag: `yocto-5.0.3`
- Git Revision: `11d83170922a2c6b9db1f6e8c23e533526984b2c`
- Release Artefact: `bitbake-11d83170922a2c6b9db1f6e8c23e533526984b2c`
- sha: `9643433748d7ed80d6334124390271929566b3bc076dad0f6e6be1ec6d753b8d`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.3/bitbake-11d83170922a2c6b9db1f6e8c23e533526984b2c.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.3/bitbake-11d83170922a2c6b9db1f6e8c23e533526984b2c.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.3`
- Git Revision: `TBD`

## 17.7.6 Release notes for Yocto-5.0.4 (Scarthgap)

### Security Fixes in Yocto-5.0.4

- apr: Fix CVE-2023-49582
- curl: Ignore CVE-2024-32928
- curl: Fix CVE-2024-7264
- expat: Fix CVE-2024-45490, CVE-2024-45491 and CVE-2024-45492
- ffmpeg: Fix CVE-2023-50008 and CVE-2024-32230
- libpcap: Fix CVE-2023-7256 and CVE-2024-8006

- libyaml: Ignore [CVE-2024-35325](#) and [CVE-2024-35326](#)
- openssl: Fix [CVE-2024-5535](#) and [CVE-2024-6119](#)
- python3-certifi: Fix [CVE-2024-39689](#)
- python3-setuptools: Fix [CVE-2024-6345](#)
- python3: Fix [CVE-2024-6232](#), [CVE-2024-7592](#), [CVE-2024-8088](#) and [CVE-2024-27034](#)
- qemu: Fix [CVE-2024-4467](#) and [CVE-2024-7409](#)
- ruby: Fix [CVE-2024-27282](#)
- tiff: Fix [CVE-2024-7006](#)
- vim: Fix [CVE-2024-41957](#), [CVE-2024-41965](#), [CVE-2024-43374](#), [CVE-2024-43790](#) and [CVE-2024-43802](#)

#### Fixes in Yocto-5.0.4

- apr: drop 0007-explicitly-link-libapr-against-pthread-to-make-gold-.patch
- apr: upgrade to 1.7.5
- bind: Fix build with the *httpstats* package config enabled
- bitbake: data\_smart: Improve performance for VariableHistory
- bluez5: remove redundant patch for MAX\_INPUT
- build-appliance-image: Update to scarthgap head revision
- buildhistory: Fix intermittent package file list creation
- buildhistory: Restoring files from preserve list
- buildhistory: Simplify intercept call sites and drop SSTATEPOSTINSTFUNC usage
- busybox: Fix cut with "-s" flag
- create-sdpx-2.2.bbclass: Switch from exists to isfile checking debugsrc
- cups: upgrade to 2.4.10
- dejagnu: Fix *LICENSE* (change to GPL-3.0-only)
- doc: features: describe distribution feature pni-name
- doc: features: remove duplicate word in distribution feature ext2
- expat: upgrade to 2.6.3
- expect-native: fix do\_compile failure with gcc-14
- gcc: Fix spurious '/' in GLIBC\_DYNAMIC\_LINKER on microblaze
- gcr: Fix *LICENSE* (change to LGPL-2.0-only)
- glibc: fix fortran header file conflict for arm
- go: upgrade to 1.22.6
- gstreamer1.0: disable flaky baseparser tests

- image\_types.bbclass: Use --force also with lz4,lzop
- initramfs-framework: fix typos
- iw: Fix *LICENSE* (change to ISC)
- libadwaita: upgrade to 1.5.2
- libcap-ng: update *SRC\_URI*
- libdnf: upgrade to 0.73.2
- libedit: Make docs generation deterministic
- libgfortran.inc: fix nativesdk-libgfortran dependencies
- librsvg: don't try to run target code at build time
- linux-firmware: add a package for ath12k firmware
- llvm: Enable libllvm for native build
- maintainers.inc: add maintainer for python(-setuptools, -smmap, -subunit, -testtools)
- mc: fix source URL
- migration-guide: add release notes for 4.0.20 and 5.0.3
- oeqa/postactions: fix exception handling
- oeqa/runtime/ssh: In case of failure, show exit code and handle -15 (SIGTERM)
- oeqa/runtime/ssh: add retry logic and sleeps to allow for slower systems
- oeqa/runtime/ssh: check for all errors at the end
- oeqa/runtime/ssh: increase the number of attempts
- oeqa/selftest/reproducible: Explicitly list virtual targets
- oeqa/utis/postactions: transfer whole archive over ssh instead of doing individual copies
- openssh: add backported header file include
- openssl: upgrade to 3.2.3
- os-release: Fix VERSION\_CODENAME in case it is empty
- poky.conf: bump version for 5.0.4
- populate\_sdk\_ext.bbclass: make sure OECORE\_NATIVE\_SYSROOT is exported.
- python3-maturin: Fix cross compilation issue for armv7l, mips64, ppc
- python3-pycryptodome(x): use python\_setuptools\_build\_meta build class
- python3: upgrade to 3.12.6
- python3: skip readline limited history tests
- qemu: backport patches to fix riscv64 build failure
- qemuboot: Trigger write\_qemuboot\_conf task on changes of kernel image realpath

- ref-manual: fix typo and move *SYSROOT\_DIRS* example
- ruby: Make docs generation deterministic
- systemd: Mitigate /var/log type mismatch issue
- systemd: Mitigate /var/tmp type mismatch issue
- tiff: Fix *LICENSE* (change to libtiff)
- u-boot.inc: Refactor do\_\* steps into functions that can be overridden
- udev-extraconf: Add collect flag to mount
- unzip: Fix *LICENSE* (change to Info-ZIP)
- util-linux: Add *PACKAGECONFIG* option (libmount-mountfd-support) to mitigate rootfs remount error
- vim: upgrade to 9.1.0698
- weston-init: fix weston not starting when xwayland is enabled
- wireless-regdb: upgrade to 2024.07.04
- wpa-supPLICant: upgrade to 2.11
- xserver-xorg: mark *CVE-2023-5574* as unpatched when xvfb enabled
- yocto-uninative: Update to 4.6 for glibc 2.40
- zip: Fix *LICENSE* (change to Info-ZIP)

#### Known Issues in Yocto-5.0.4

- N/A

#### Contributors to Yocto-5.0.4

- Alban Bedel
- Alexander Kanavin
- Alexis Lothoré
- Archana Polampalli
- Ashish Sharma
- Bartosz Golaszewski
- Benjamin Szőke
- Changqing Li
- Chen Qi
- Colin McAllister
- Daniel Semkowicz
- Dmitry Baryshkov
- Gauthier HADERER

- Guðni Már Gilbert
- Jon Mason
- Jose Quaresma
- Jörg Sommer
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Mark Hatle
- Martin Jansa
- Matthias Pritschet
- Michael Halstead
- Mingli Yu
- Niko Mauno
- Pedro Ferreira
- Peter Marko
- Quentin Schulz
- Richard Purdie
- Robert Yang
- Ross Burton
- Ryan Eatmon
- Siddharth Doshi
- Simone Weiß
- Soumya Sambu
- Steve Sakoman
- Trevor Gamblin
- Ulrich Ölmann
- Vijay Anusuri
- Wang Mingyu
- Weisser, Pascal.ext
- Yogita Urade



## Repositories / Downloads for Yocto-5.0.4

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.4`
- Git Revision: `2034fc38eb4e63984d9bd6b260aa1bf95ce562e4`
- Release Artefact: `poky-2034fc38eb4e63984d9bd6b260aa1bf95ce562e4`
- sha: `697ed099793d6c86d5ffe590e96f99689bd28dcb2d4451dc4585496fa4a20400`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.4/poky-2034fc38eb4e63984d9bd6b260aa1bf95ce562e4.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.4/poky-2034fc38eb4e63984d9bd6b260aa1bf95ce562e4.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.4`
- Git Revision: `f888dd911529a828820799a7a1b75dfd3a44847c`
- Release Artefact: `oecore-f888dd911529a828820799a7a1b75dfd3a44847c`
- sha: `93cb4c3c8e0f77edab20814d155847dc3452c6b083e3dd9c7a801e80a7e4d228`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.4/oecore-f888dd911529a828820799a7a1b75dfd3a44847c.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.4/oecore-f888dd911529a828820799a7a1b75dfd3a44847c.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.4`
- Git Revision: `acbba477893ef87388effc4679b7f40ee49fc852`
- Release Artefact: `meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852`
- sha: `3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.4/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.4/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.8`

- Tag: `yocto-5.0.4`
- Git Revision: `d251668d9a7a8dd25bd8767efb30d6d9ff8b1ad3`
- Release Artefact: `bitbake-d251668d9a7a8dd25bd8767efb30d6d9ff8b1ad3`
- sha: `d873f4d3a471d26680dc39200d8f3851a6863f15daa9bed978ba31b930f9a1c1`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-5.0.4/bitbake-d251668d9a7a8dd25bd8767efb30d6d9ff8b1ad3.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-5.0.4/bitbake-d251668d9a7a8dd25bd8767efb30d6d9ff8b1ad3.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.4`
- Git Revision: `d71081dd14a9d75ace4d1c62472374f37b4a888d`

## 17.7.7 Release notes for Yocto-5.0.5 (Scarthgap)

### Security Fixes in Yocto-5.0.5

- cups: Fix CVE-2024-47175
- curl: Fix CVE-2024-8096
- gnupg: Ignore CVE-2022-3219 (wont-fix)
- libarchive: Fix CVE-2024-48957 and CVE-2024-48958
- openssh: Ignore CVE-2023-51767 (wont-fix)
- openssl: Fix CVE-2024-9143
- ruby: Fix CVE-2024-41123 and CVE-2024-41496
- rust-llvm: Fix CVE-2024-0151
- rust, libstd-rs: Ignore CVE-2024-43402
- wpa-supPLICANT: Patch SAE H2E and incomplete downgrade protection for group negotiation
- wpa-supPLICANT: Fix CVE-2024-3596
- wpa-supPLICANT: Ignore CVE-2024-5290

### Fixes in Yocto-5.0.5

- binutils: stable 2.42 branch updates
- bitbake.conf: Add truncate to *HOSTTOOLS*
- bitbake: asynrcp: Use client timeout for websocket open timeout
- bitbake: bitbake: doc/user-manual: Update the *BB\_HASHSERVE\_UPSTREAM*
- bitbake: git-sm: Add `call_process_submodules()` to remove duplicated code

- bitbake: git-sm: Remove downloads/tmpdir when failed
- bitbake: tests/fetch: Use our own mirror of mobile-broadband-provider to decouple from gnome gitlab
- bitbake: tests/fetch: Use our own mirror of sysprof to decouple from gnome gitlab
- build-appliance-image: Update to scarthgap head revision
- cryptodev: upgrade to 1.14
- cve-check: add support for cvss v4.0
- cve\_check: Use a local copy of the database during builds
- dev-manual: add bblock documentation
- documentation: conf.py: rename :cve: role to :cve\_nist:
- documentation: README: add instruction to run Vale on a subset
- documentation: Makefile: add SPHINXLINTDOCS to specify subset to sphinx-lint
- e2fsprogs: removed 'sed -u' option
- ffmpeg: Add "libswresample libavcodec" to *CVE\_PRODUCT*
- glibc: stable 2.39 branch updates.
- go: upgrade to 1.22.8
- icu: update patch Upstream-Status
- image.bbclass: Drop support for ImageQAFailed exceptions in image\_qa
- image\_qa: fix error handling
- install-buildtools: fix "test installation" step
- install-buildtools: remove md5 checksum validation
- install-buildtools: update base-url, release and installer version
- kernel-devsrc: remove 64 bit vdso cmd files
- kernel-fitimage: fix external dtb check
- kernel-fitimage: fix intantation
- lib/oe/package-manager: skip processing installed-pkgs with empty globs
- liba52: fix do\_fetch error
- libpcre2: Update base uri PhilipHazel -> PCRE2Project
- libsndl2: Fix non-deterministic configure option for libsamplerate
- license: Fix directory layout issues
- linux-firmware: upgrade to 20240909
- linux-yocto/6.6: fix genericarm64 config warning
- linux-yocto/6.6: upgrade to v6.6.54

- lsb-release: fix Distro Codename shell escaping
- madevs: Fix issue when rootdir of / is given
- madevs: Fix matching uid/gid
- meta-ide-support: Mark recipe as MACHINE-specific
- meta-world-pkgdata: Inherit nopackages
- migration-guide: add release notes for 4.0.21, 4.0.22 and 5.0.4
- migration-guide: release-notes-4.0: update *BB\_HASHSERVE\_UPSTREAM* for new infrastructure
- migration-guide: release-notes-5.0.rst: update NO\_OUTPUT -> NO\_COLOR
- orc: upgrade to 0.4.40
- overview-manual: concepts: add details on package splitting
- poky.conf: bump version for 5.0.5
- populate\_sdk\_base: inherit nopackages
- ptest-runner: upgrade to 2.4.5
- pulseaudio: correct freedesktop.org -> www.freedesktop.org *SRC\_URI*
- desktop-file-utils: correct freedesktop.org -> www.freedesktop.org *SRC\_URI*
- python3-lxml: upgrade to v5.0.2
- python3-setuptools: Add "python:setuptools" to *CVE\_PRODUCT*
- recipes-bsp: usbutils: Fix usb-devices command using busybox
- ref-manual: add missing *CVE\_CHECK* manifest variables
- ref-manual: add missing *EXTERNAL\_KERNEL\_DEVICETREE* variable
- ref-manual: add missing *OPKGBUILDCMD* variable
- ref-manual: add missing *TESTIMAGE\_FAILED\_QA\_ARTIFACTS*
- ref-manual: devtool-reference: document missing commands
- ref-manual: devtool-reference: refresh example outputs
- ref-manual: faq: add q&a on class appends
- ref-manual: introduce *CVE\_CHECK\_REPORT\_PATCHED* variable
- ref-manual: merge patch-status-\* to patch-status
- ref-manual: release-process: add a reference to the doc's release
- ref-manual: release-process: refresh the current LTS releases
- ref-manual: release-process: update releases.svg
- ref-manual: release-process: update releases.svg with month after "Current"
- ref-manual: structure.rst: document missing tmp/ dirs

- ref-manual: variables: add SIGGEN\_LOCKEDSIGS\* variables
- rootfs-postcommands.bbclass: make opkg status reproducible
- rpm: fix expansion of %\_libdir in macros
- ruby: upgrade to 3.3.5
- runqemu: Fix detection of -serial parameter
- runqemu: keep generating tap devices
- scripts/install-buildtools: Update to 5.0.3
- sqlite3: upgrade to 3.45.3
- styles: vocabularies: Yocto: add sstate
- systemtap: fix systemtap-native build error on Fedora 40
- sysvinit: take release tarballs from github
- testexport: fallback for empty *IMAGE\_LINK\_NAME*
- testimage: fallback for empty *IMAGE\_LINK\_NAME*
- uboot-sign: fix counters in do\_uboot\_assemble\_fitimage
- vim: upgrade to 9.1.0764
- virglrenderer: Add patch to fix -int-conversion build issue
- webkitgtk: upgrade to 2.44.3
- weston: backport patch to allow neatvnc < v0.9.0
- wpa-suplicant: Patch security advisory 2024-2
- xserver-xorg: upgrade to 21.1.14

### Known Issues in Yocto-5.0.5

- oega/runtime: the beaglebone-yocto target fails the parselogs runtime test due to unexpected kernel error messages in the log (see [bug 15624](#) on Bugzilla).

### Contributors to Yocto-5.0.5

- Aditya Tayade
- Adrian Freihofer
- Aleksandar Nikolic
- Alexander Kanavin
- Antonin Godard
- Anuj Mittal
- Bruce Ashfield
- Claus Stovgaard

- Deepesh Varatharajan
- Deepthi Hemraj
- Hiago De Franco
- Hitendra Prajapati
- Jaeyoon Jung
- Jiaying Song
- Jonas Gorski
- Jose Quaresma
- Joshua Watt
- Julien Stephan
- Jörg Sommer
- Khem Raj
- Konrad Weihmann
- Lee Chee Yang
- Louis Rannou
- Macpaul Lin
- Martin Jansa
- Paul Barker
- Paul Gerber
- Peter Kjellerstedt
- Peter Marko
- Purushottam Choudhary
- Richard Purdie
- Robert Yang
- Rohini Sangam
- Ross Burton
- Sergei Zhmylev
- Shunsuke Tokumoto
- Steve Sakoman
- Teresa Remmet
- Victor Kamensky
- Vijay Anusuri

- Wang Mingyu
- Yi Zhao
- Yogita Urade
- Zahir Hussain

## Repositories / Downloads for Yocto-5.0.5

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.5`
- Git Revision: `dce4163d42f7036ea216b52b9135968d51bec4c1`
- Release Artefact: `poky-dce4163d42f7036ea216b52b9135968d51bec4c1`
- sha: `ad35a965a284490a962f6854ace536b8795f96514e14bf5c79f91f6d76ac25d3`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.5/poky-dce4163d42f7036ea216b52b9135968d51bec4c1.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.5/poky-dce4163d42f7036ea216b52b9135968d51bec4c1.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.5`
- Git Revision: `a051a066da2874b95680d0353dfa18c1d56b2670`
- Release Artefact: `oecore-a051a066da2874b95680d0353dfa18c1d56b2670`
- sha: `16d252aade00161ade2692f41b2da3effeb1f41816a66db843bb1c5495125e93`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.5/oecore-a051a066da2874b95680d0353dfa18c1d56b2670.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.5/oecore-a051a066da2874b95680d0353dfa18c1d56b2670.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.5`
- Git Revision: `acbba477893ef87388effc4679b7f40ee49fc852`
- Release Artefact: `meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852`
- sha: `3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c`

- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.5/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.5/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake/>
- Branch: 2.8
- Tag: yocto-5.0.5
- Git Revision: 377eba2361850adfb8ce7e761ef9c76be287f88c
- Release Artefact: bitbake-377eba2361850adfb8ce7e761ef9c76be287f88c
- sha: 4a5a35098eec719bbb879706d50e552a2b709295db4055c8050ae7dda1eb2994
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.5/bitbake-377eba2361850adfb8ce7e761ef9c76be287f88c.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.5/bitbake-377eba2361850adfb8ce7e761ef9c76be287f88c.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: scarthgap
- Tag: yocto-5.0.5
- Git Revision: e882cb3e5816d081eb05cb83488f286cca70e0c6

## 17.7.8 Release notes for Yocto-5.0.6 (Scarthgap)

### Security Fixes in Yocto-5.0.6

- acpica: Fix CVE-2024-24856
- curl: Fix CVE-2024-9681
- dropbear: Fix CVE-2023-48795
- expat: Fix CVE-2024-50602
- ffmpeg: Fix CVE-2023-49501, CVE-2023-49528, CVE-2023-50007, CVE-2024-7055 and CVE-2024-28661
- glib-2.0: Fix CVE-2024-52533
- ghostscript: Fix CVE-2024-46951, CVE-2024-46952, CVE-2024-46953, CVE-2024-46954, CVE-2024-46955 and CVE-2024-46956
- gstreamer1.0: Ignore CVE-2024-0444
- libpam: Fix CVE-2024-10041
- libsndfile: Fix CVE-2024-50612
- libsoup: Fix CVE-2024-52530, CVE-2024-52531 and CVE-2024-52532



- ovmf: Fix [CVE-2024-1298](#) and [CVE-2024-38796](#)
- python3-zipp: Fix [CVE-2024-5569](#)
- qemu: Fix [CVE-2024-4693](#), [CVE-2024-6505](#) and [CVE-2024-7730](#)
- qemu: Ignore [CVE-2024-6505](#)

### Fixes in Yocto-5.0.6

- binutils: Add missing perl modules to *RDEPENDS* for nativesdk variant
- binutils: stable 2.42 branch update
- bitbake: Remove custom exception backtrace formatting
- bitbake: fetch2/git: Use quote from shlex, not pipes
- bitbake: fetch2: use persist\_data context managers
- bitbake: fetch/wget: Increase timeout to 100s from 30s
- bitbake: persist\_data: close connection in SQLTable \_\_exit\_\_
- bitbake: runqueue: Fix performance of multiconfigs with large overlap
- bitbake: runqueue: Fix scenetask processing performance issue
- bitbake: runqueue: Optimise setscene loop processing
- build-appliance-image: Update to scarthgap head revision
- builder: set *CVE\_PRODUCT*
- cmake: Fix sporadic issues when determining compiler internals
- cml1: do\_diffconfig: Don't override .config with .config.orig
- contributor-guide: Remove duplicated words
- dev-manual: bblock: use warning block instead of attention
- dev-manual: document how to provide confs from layer.conf
- dnf: drop python3-iniparse from *DEPENDS* and *RDEPENDS*
- do\_package/ssstate/ssstatesig: Change timestamp clamping to hash output only
- doc: Makefile: add support for xelatex
- doc: Makefile: publish pdf and epub versions too
- doc: Makefile: remove inkscape, replace by rsvg-convert
- doc: add a download page for epub and pdf
- doc: conf.py: add a bitbake\_git extlink
- doc: standards.md: add a section on admonitions
- doc: sphinx-static: switchers.js.in: do not refer to URL\_ROOT anymore
- dropbear: backport fix for concurrent channel open/close

- enchant2: fix do\_fetch error
- expat: upgrade to 2.6.4
- gcc: backport patch to fix an issue with tzdata 2024b
- ghostscript: upgrade to 10.04.0
- glibc: stable 2.39 branch updates
- groff: fix rare build race in hdtbl
- libgcrypt: Fix building error with '-O2' in sysroot path
- libpam: drop cracklib from *DEPENDS*
- libxml-parser-perl: fix do\_fetch error
- llvm: reduce size of -dbg package
- lttnng-ust: backport patch to fix cmake-multiple-shared-libraries build error
- migration-guides: add release notes for 4.0.23 and 5.0.5
- ninja: fix build with python 3.13
- oeqa/runtime/ssh: Fix incorrect timeout fix
- oeqa/runtime/ssh: Rework ssh timeout
- oeqa/utis/gitarchive: Return tag name and improve exclude handling
- package\_rpm: Check if file exists before open()
- package\_rpm: restrict rpm to 4 threads
- package\_rpm: use zstd's default compression level
- poky.conf: bump version for 5.0.6
- pseudo: Fix envp bug and add posix\_spawn wrapper
- python3-poetry-core: drop python3-six from *RDEPENDS*
- python3-requests: upgrade to 2.32.2
- python3-urllib3: upgrade to 2.2.2
- qemu: upgrade to 8.2.7
- qemurunner: Clean up serial\_lock handling
- ref-manual: classes: fix bin\_package description
- resulttool: Add --logfile-archive option to store mode
- resulttool: Allow store to filter to specific revisions
- resulttool: Clean up reproducible build logs
- resulttool: Fix passthrough of --all files in store mode
- resulttool: Handle ltp rawlogs as well as ptest

- resulttool: Improve repo layout for oeselftest results
- resulttool: Trim the precision of duration information
- resulttool: Use single space indentation in json output
- rootfs: Ensure run-postinsts is not uninstalled for read-only-rootfs-delayed-postinsts
- rxvt-unicode.inc: disable the terminfo installation by setting TIC to :
- sanity: check for working user namespaces
- scripts/install-buildtools: Update to 5.0.5
- selftest/reproducible: Clean up pathnames
- selftest/reproducible: Drop rawlogs
- shared-mime-info: drop itstool-native from *DEPENDS*
- strace: download release tarballs from GitHub
- systemd-boot: drop intltool-native from *DEPENDS*
- systemd: drop intltool-native from *DEPENDS*
- systemd: upgrade to 255.13
- sysvinit: backport patch for fixing one issue of pidof
- tcl: skip io-13.6 test case
- toolchain-shar-extract.sh: exit when post-relocate-setup.sh fails
- tune-cortexa32: set tune feature as armv8a
- tzcode-native: upgrade to 2024b
- tzdata: upgrade to 2024b
- uboot-sign: fix concat\_dtb arguments
- udev-extraconf: fix network.sh script did not configure hotplugged interfaces
- webkitgtk: fix erroneous use of unsupported DEBUG\_LEVELFLAG variable
- wireless-regdb: upgrade to 2024.10.07

### Known Issues in Yocto-5.0.6

- N/A

### Contributors to Yocto-5.0.6

Thanks to the following people who contributed to this release:

- Aleksandar Nikolic
- Alexander Kanavin
- Antonin Godard
- Archana Polampalli

- Bin Lan
- Changqing Li
- Chen Qi
- Chris Laplante
- Clayton Casciato
- Deepthi Hemraj
- Divya Chellam
- Florian Kreutzer
- Gassner, Tobias.ext
- Guðni Már Gilbert
- Harish Sadineni
- Hitendra Prajapati
- Hongxu Jia
- Jagadeesh Krishnanjanappa
- Jiaying Song
- Jinfeng Wang
- Joshua Watt
- Lee Chee Yang
- Markus Volk
- Michael Opdenacker
- Pavel Zhukov
- Peter Marko
- Philip Lorenz
- Randy MacLeod
- Regis Dargent
- Richard Purdie
- Robert Yang
- Ross Burton
- Soumya Sambu
- Steve Sakoman
- Talel BELHAJSALEM
- Trevor Gamblin

- Vijay Anusuri
- Wang Mingyu
- Yogita Urade

## Repositories / Downloads for Yocto-5.0.6

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.6`
- Git Revision: `2541a8171f91812a4b16e7dc4da0d77d2318a256`
- Release Artefact: `poky-2541a8171f91812a4b16e7dc4da0d77d2318a256`
- sha: `b77157596ae75d163387a08a317397a57ab8fa6cf4725f28e344fae3f69cca4d`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.6/poky-2541a8171f91812a4b16e7dc4da0d77d2318a256.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.6/poky-2541a8171f91812a4b16e7dc4da0d77d2318a256.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.6`
- Git Revision: `336eec6808710f260a5336ca8ca98139a80ccb14`
- Release Artefact: `oecore-336eec6808710f260a5336ca8ca98139a80ccb14`
- sha: `38c4fa7e7e88c28361c012dd5baabe373e2ec3c8aba6194146768b146192cceb`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.6/oecore-336eec6808710f260a5336ca8ca98139a80ccb14.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.6/oecore-336eec6808710f260a5336ca8ca98139a80ccb14.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.6`
- Git Revision: `acbba477893ef87388effc4679b7f40ee49fc852`
- Release Artefact: `meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852`
- sha: `3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.6/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.6/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0.6
- Git Revision: f40a3a477d5241b697bf2fb030dd804c1ff5839f
- Release Artefact: bitbake-f40a3a477d5241b697bf2fb030dd804c1ff5839f
- sha: dbfc056c7408a5547f624799621ab1261a05685112e0922a88007723b1edbc87
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.6/bitbake-f40a3a477d5241b697bf2fb030dd804c1ff5839f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.6/bitbake-f40a3a477d5241b697bf2fb030dd804c1ff5839f.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: scarthgap
- Tag: yocto-5.0.6
- Git Revision: TBD

## 17.7.9 Release notes for Yocto-5.0.7 (Scarthgap)

### Security Fixes in Yocto-5.0.7

- avahi: Fix CVE-2024-52616
- binutils: Fix CVE-2024-53589
- ffmpeg: Fix CVE-2024-35366, CVE-2024-35367 and CVE-2024-35368
- gstreamer1.0-plugins-base: Fix CVE-2024-47538, CVE-2024-47541, CVE-2024-47542, CVE-2024-47600, CVE-2024-47607, CVE-2024-47615 and CVE-2024-47835
- gstreamer1.0-plugins-good: Fix CVE-2024-47537, CVE-2024-47539, CVE-2024-47540, CVE-2024-47543, CVE-2024-47544, CVE-2024-47545, CVE-2024-47546, CVE-2024-47596, CVE-2024-47597, CVE-2024-47598, CVE-2024-47599, CVE-2024-47601, CVE-2024-47602, CVE-2024-47603, CVE-2024-47606, CVE-2024-47613, CVE-2024-47774, CVE-2024-47775, CVE-2024-47776, CVE-2024-47777, CVE-2024-47778 and CVE-2024-47834
- gstreamer1.0: Ignore CVE-2024-47537, CVE-2024-47539, CVE-2024-47540, CVE-2024-47543, CVE-2024-47544, CVE-2024-47545, CVE-2024-47538, CVE-2024-47541, CVE-2024-47542, CVE-2024-47600, CVE-2024-47607, CVE-2024-47615, CVE-2024-47835, CVE-2024-47546, CVE-2024-47596, CVE-2024-47597, CVE-2024-47598, CVE-2024-47599, CVE-2024-47601, CVE-2024-47602, CVE-2024-47603, CVE-2024-47613, CVE-2024-47774, CVE-2024-47775, CVE-2024-47776, CVE-2024-47777, CVE-2024-47778 and CVE-2024-47834
- libarchive: Fix CVE-2024-20696
- libxml2: Fix CVE-2024-40896

- [linux-yocto/6.6](#): Fix [CVE-2024-27059](#), [CVE-2024-43098](#), [CVE-2024-45828](#), [CVE-2024-47141](#), [CVE-2024-47143](#), [CVE-2024-47704](#), [CVE-2024-47809](#), [CVE-2024-48873](#), [CVE-2024-48875](#), [CVE-2024-48881](#), [CVE-2024-49863](#), [CVE-2024-49864](#), [CVE-2024-49866](#), [CVE-2024-49867](#), [CVE-2024-49868](#), [CVE-2024-49870](#), [CVE-2024-49871](#), [CVE-2024-49874](#), [CVE-2024-49875](#), [CVE-2024-49877](#), [CVE-2024-49878](#), [CVE-2024-49879](#), [CVE-2024-49881](#), [CVE-2024-49882](#), [CVE-2024-49883](#), [CVE-2024-49884](#), [CVE-2024-49886](#), [CVE-2024-49889](#), [CVE-2024-49890](#), [CVE-2024-49892](#), [CVE-2024-49894](#), [CVE-2024-49895](#), [CVE-2024-49896](#), [CVE-2024-49900](#), [CVE-2024-49901](#), [CVE-2024-49902](#), [CVE-2024-49903](#), [CVE-2024-49905](#), [CVE-2024-49907](#), [CVE-2024-49912](#), [CVE-2024-49913](#), [CVE-2024-49924](#), [CVE-2024-49925](#), [CVE-2024-49927](#), [CVE-2024-49929](#), [CVE-2024-49930](#), [CVE-2024-49931](#), [CVE-2024-49933](#), [CVE-2024-49935](#), [CVE-2024-49936](#), [CVE-2024-49937](#), [CVE-2024-49938](#), [CVE-2024-49939](#), [CVE-2024-49944](#), [CVE-2024-49946](#), [CVE-2024-49947](#), [CVE-2024-49948](#), [CVE-2024-49949](#), [CVE-2024-49950](#), [CVE-2024-49951](#), [CVE-2024-49952](#), [CVE-2024-49953](#), [CVE-2024-49954](#), [CVE-2024-49955](#), [CVE-2024-49957](#), [CVE-2024-49958](#), [CVE-2024-49959](#), [CVE-2024-49960](#), [CVE-2024-49961](#), [CVE-2024-49962](#), [CVE-2024-49963](#), [CVE-2024-49965](#), [CVE-2024-49966](#), [CVE-2024-49969](#), [CVE-2024-49973](#), [CVE-2024-49975](#), [CVE-2024-49976](#), [CVE-2024-49977](#), [CVE-2024-49978](#), [CVE-2024-49980](#), [CVE-2024-49981](#), [CVE-2024-49982](#), [CVE-2024-49983](#), [CVE-2024-49985](#), [CVE-2024-49986](#), [CVE-2024-49987](#), [CVE-2024-49988](#), [CVE-2024-49989](#), [CVE-2024-49991](#), [CVE-2024-49992](#), [CVE-2024-49995](#), [CVE-2024-49996](#), [CVE-2024-49997](#), [CVE-2024-50000](#), [CVE-2024-50001](#), [CVE-2024-50002](#), [CVE-2024-50003](#), [CVE-2024-50005](#), [CVE-2024-50006](#), [CVE-2024-50007](#), [CVE-2024-50008](#), [CVE-2024-50012](#), [CVE-2024-50013](#), [CVE-2024-50015](#), [CVE-2024-50016](#), [CVE-2024-50019](#), [CVE-2024-50022](#), [CVE-2024-50023](#), [CVE-2024-50024](#), [CVE-2024-50026](#), [CVE-2024-50029](#), [CVE-2024-50031](#), [CVE-2024-50032](#), [CVE-2024-50033](#), [CVE-2024-50035](#), [CVE-2024-50036](#), [CVE-2024-50038](#), [CVE-2024-50039](#), [CVE-2024-50040](#), [CVE-2024-50041](#), [CVE-2024-50044](#), [CVE-2024-50045](#), [CVE-2024-50046](#), [CVE-2024-50047](#), [CVE-2024-50048](#), [CVE-2024-50049](#), [CVE-2024-50051](#), [CVE-2024-50055](#), [CVE-2024-50057](#), [CVE-2024-50058](#), [CVE-2024-50059](#), [CVE-2024-50060](#), [CVE-2024-50061](#), [CVE-2024-50062](#), [CVE-2024-50063](#), [CVE-2024-50064](#), [CVE-2024-50065](#), [CVE-2024-50066](#), [CVE-2024-50069](#), [CVE-2024-50070](#), [CVE-2024-50072](#), [CVE-2024-50073](#), [CVE-2024-50074](#), [CVE-2024-50075](#), [CVE-2024-50076](#), [CVE-2024-50077](#), [CVE-2024-50078](#), [CVE-2024-50080](#), [CVE-2024-50082](#), [CVE-2024-50083](#), [CVE-2024-50084](#), [CVE-2024-50085](#), [CVE-2024-50086](#), [CVE-2024-50087](#), [CVE-2024-50088](#), [CVE-2024-50093](#), [CVE-2024-50095](#), [CVE-2024-50096](#), [CVE-2024-50098](#), [CVE-2024-50099](#), [CVE-2024-50101](#), [CVE-2024-50103](#), [CVE-2024-50108](#), [CVE-2024-50110](#), [CVE-2024-50111](#), [CVE-2024-50112](#), [CVE-2024-50115](#), [CVE-2024-50116](#), [CVE-2024-50117](#), [CVE-2024-50120](#), [CVE-2024-50121](#), [CVE-2024-50124](#), [CVE-2024-50125](#), [CVE-2024-50126](#), [CVE-2024-50127](#), [CVE-2024-50128](#), [CVE-2024-50130](#), [CVE-2024-50131](#), [CVE-2024-50133](#), [CVE-2024-50134](#), [CVE-2024-50135](#), [CVE-2024-50136](#), [CVE-2024-50139](#), [CVE-2024-50140](#), [CVE-2024-50141](#), [CVE-2024-50142](#), [CVE-2024-50143](#), [CVE-2024-50145](#), [CVE-2024-50147](#), [CVE-2024-50148](#), [CVE-2024-50150](#), [CVE-2024-50151](#), [CVE-2024-50152](#), [CVE-2024-50153](#), [CVE-2024-50154](#), [CVE-2024-50155](#), [CVE-2024-50156](#), [CVE-2024-50158](#), [CVE-2024-50159](#), [CVE-2024-50160](#), [CVE-2024-50162](#), [CVE-2024-50163](#), [CVE-2024-50164](#), [CVE-2024-50166](#), [CVE-2024-50167](#), [CVE-2024-50168](#), [CVE-2024-50169](#), [CVE-2024-50170](#), [CVE-2024-50171](#), [CVE-2024-50172](#), [CVE-2024-50175](#), [CVE-2024-50176](#), [CVE-2024-50179](#), [CVE-2024-50180](#), [CVE-2024-50181](#), [CVE-2024-50182](#), [CVE-2024-50183](#), [CVE-2024-50184](#), [CVE-2024-50185](#), [CVE-2024-50186](#), [CVE-2024-50187](#), [CVE-2024-50188](#), [CVE-2024-50189](#), [CVE-2024-50191](#), [CVE-2024-50192](#), [CVE-2024-50193](#), [CVE-2024-50194](#), [CVE-2024-50195](#), [CVE-2024-50196](#), [CVE-2024-50198](#), [CVE-2024-50201](#), [CVE-2024-50202](#), [CVE-2024-50205](#), [CVE-2024-50208](#), [CVE-2024-50209](#), [CVE-2024-50211](#), [CVE-2024-50215](#), [CVE-2024-50222](#), [CVE-2024-50223](#), [CVE-2024-50224](#), [CVE-2024-50226](#), [CVE-2024-50229](#), [CVE-2024-50230](#), [CVE-2024-50231](#), [CVE-2024-50232](#), [CVE-2024-50233](#),

CVE-2024-50234, CVE-2024-50235, CVE-2024-50236, CVE-2024-50237, CVE-2024-50239, CVE-2024-50240, CVE-2024-50242, CVE-2024-50243, CVE-2024-50244, CVE-2024-50245, CVE-2024-50246, CVE-2024-50247, CVE-2024-50248, CVE-2024-50249, CVE-2024-50250, CVE-2024-50251, CVE-2024-50252, CVE-2024-50255, CVE-2024-50256, CVE-2024-50257, CVE-2024-50258, CVE-2024-50259, CVE-2024-50261, CVE-2024-50262, CVE-2024-50264, CVE-2024-50265, CVE-2024-50267, CVE-2024-50268, CVE-2024-50269, CVE-2024-50271, CVE-2024-50272, CVE-2024-50273, CVE-2024-50275, CVE-2024-50276, CVE-2024-50278, CVE-2024-50279, CVE-2024-50282, CVE-2024-50283, CVE-2024-50284, CVE-2024-50285, CVE-2024-50286, CVE-2024-50287, CVE-2024-50292, CVE-2024-50296, CVE-2024-50298, CVE-2024-50299, CVE-2024-50300, CVE-2024-50301, CVE-2024-50302, CVE-2024-53042, CVE-2024-53043, CVE-2024-53046, CVE-2024-53047, CVE-2024-53052, CVE-2024-53055, CVE-2024-53057, CVE-2024-53058, CVE-2024-53059, CVE-2024-53060, CVE-2024-53061, CVE-2024-53063, CVE-2024-53066, CVE-2024-53068, CVE-2024-53072, CVE-2024-53076, CVE-2024-53079, CVE-2024-53081, CVE-2024-53082, CVE-2024-53083, CVE-2024-53088, CVE-2024-53091, CVE-2024-53093, CVE-2024-53094, CVE-2024-53096, CVE-2024-53099, CVE-2024-53100, CVE-2024-53101, CVE-2024-53103, CVE-2024-53108, CVE-2024-53109, CVE-2024-53110, CVE-2024-53112, CVE-2024-53113, CVE-2024-53119, CVE-2024-53120, CVE-2024-53121, CVE-2024-53122, CVE-2024-53123, CVE-2024-53126, CVE-2024-53127, CVE-2024-53129, CVE-2024-53130, CVE-2024-53131, CVE-2024-53134, CVE-2024-53135, CVE-2024-53138, CVE-2024-53139, CVE-2024-53140, CVE-2024-53141, CVE-2024-53142, CVE-2024-53145, CVE-2024-53146, CVE-2024-53150, CVE-2024-53151, CVE-2024-53154, CVE-2024-53155, CVE-2024-53156, CVE-2024-53157, CVE-2024-53161, CVE-2024-53165, CVE-2024-53166, CVE-2024-53168, CVE-2024-53171, CVE-2024-53173, CVE-2024-53175, CVE-2024-53180, CVE-2024-53188, CVE-2024-53191, CVE-2024-53200, CVE-2024-53202, CVE-2024-53208, CVE-2024-53210, CVE-2024-53213, CVE-2024-53215, CVE-2024-53217, CVE-2024-53224, CVE-2024-53226, CVE-2024-53227, CVE-2024-53230, CVE-2024-53231, CVE-2024-53237, CVE-2024-53239, CVE-2024-54683, CVE-2024-55916, CVE-2024-56369, CVE-2024-56538, CVE-2024-56551, CVE-2024-56567, CVE-2024-56568, CVE-2024-56569, CVE-2024-56572, CVE-2024-56574, CVE-2024-56575, CVE-2024-56577, CVE-2024-56578, CVE-2024-56579, CVE-2024-56581, CVE-2024-56587, CVE-2024-56593, CVE-2024-56595, CVE-2024-56596, CVE-2024-56598, CVE-2024-56600, CVE-2024-56601, CVE-2024-56602, CVE-2024-56603, CVE-2024-56604, CVE-2024-56605, CVE-2024-56606, CVE-2024-56611, CVE-2024-56613, CVE-2024-56614, CVE-2024-56615, CVE-2024-56617, CVE-2024-56622, CVE-2024-56623, CVE-2024-56626, CVE-2024-56627, CVE-2024-56629, CVE-2024-56631, CVE-2024-56634, CVE-2024-56635, CVE-2024-56640, CVE-2024-56642, CVE-2024-56643, CVE-2024-56648, CVE-2024-56649, CVE-2024-56650, CVE-2024-56651, CVE-2024-56653, CVE-2024-56654, CVE-2024-56657, CVE-2024-56658, CVE-2024-56659, CVE-2024-56660, CVE-2024-56662, CVE-2024-56663, CVE-2024-56664, CVE-2024-56667, CVE-2024-56670, CVE-2024-56672, CVE-2024-56675, CVE-2024-56687, CVE-2024-56688, CVE-2024-56689, CVE-2024-56692, CVE-2024-56694, CVE-2024-56698, CVE-2024-56704, CVE-2024-56708, CVE-2024-56710, CVE-2024-56715, CVE-2024-56716, CVE-2024-56717, CVE-2024-56718, CVE-2024-56720, CVE-2024-56722, CVE-2024-56723, CVE-2024-56724, CVE-2024-56725, CVE-2024-56726, CVE-2024-56727, CVE-2024-56728, CVE-2024-56729, CVE-2024-56739, CVE-2024-56741, CVE-2024-56744, CVE-2024-56745, CVE-2024-56746, CVE-2024-56747, CVE-2024-56748, CVE-2024-56751, CVE-2024-56752, CVE-2024-56754, CVE-2024-56755, CVE-2024-56756, CVE-2024-56760, CVE-2024-56763, CVE-2024-56765, CVE-2024-56767, CVE-2024-56769, CVE-2024-56770, CVE-2024-56774, CVE-2024-56776, CVE-2024-56777, CVE-2024-56778, CVE-2024-56779, CVE-2024-56780, CVE-2024-56781, CVE-2024-56783, CVE-2024-56785, CVE-2024-56786, CVE-2024-56787, CVE-2024-57798, CVE-2024-57807 and CVE-2024-57874



- ofono: Fix [CVE-2023-4232](#), [CVE-2023-4235](#), [CVE-2024-7539](#), [CVE-2024-7540](#), [CVE-2024-7541](#), [CVE-2024-7542](#), [CVE-2024-7543](#), [CVE-2024-7544](#), [CVE-2024-7545](#), [CVE-2024-7546](#) and [CVE-2024-7547](#)
- rsync: Fix [CVE-2024-12084](#), [CVE-2024-12085](#), [CVE-2024-12086](#), [CVE-2024-12087](#), [CVE-2024-12088](#) and [CVE-2024-12747](#)
- socat: Fix [CVE-2024-54661](#)
- subversion: Fix [CVE-2024-46901](#)
- wget: Fix [CVE-2024-10524](#)

### Fixes in Yocto-5.0.7

- bitbake: cooker: Make cooker 'skiplist' per-multiconfig/mc
- bitbake: tests/fetch: Fix git shallow test failure with git >= 2.48
- bitbake: ui/knotty: print log paths for failed tasks in summary
- bitbake: ui/knotty: respect NO\_COLOR & check for tty; rename print\_hyperlink => format\_hyperlink
- bluez5: Revert "bluez5: remove configuration files from install task"
- bluez5: backport patch to fix address type when loading keys
- boost: fix do\_fetch error
- build-appliance-image: Update to scarthgap head revision
- classes/nativesdk: also override *TUNE\_PKGARCH*
- classes/qemu: use tune to select QEMU\_EXTRAOPTIONS, not package architecture
- contributor-guide/submit-changes.rst: suggest to remove the git signature
- cve-update-nvd2-native: Handle *BB\_NO\_NETWORK* and missing db
- cve-update-nvd2-native: Tweak to work better with NFS *DL\_DIR*
- dev-manual/bmaptool.rst: correct command for bmaptool-native
- dev-manual/bmaptool.rst: simplify and fix instructions
- dev-manual: fix styling of references to bmaptool
- docs: Gather dependencies in poky.yaml.in
- docs: Update autobuilder URLs to valkyrie
- docs: Update the documentation for *SRCPV*
- gcc: Fix c++: tweak for Wrangle-loop-construct
- groff: Fix race issues for parallel build
- libgfortran: fix buildpath QA issue
- libxml2: Upgrade to 2.12.9
- linux-yocto/6.6: bsp/genericarm64: disable ARM64\_SME
- linux-yocto/6.6: genericarm64.cfg: enable CONFIG\_DMA\_CMA

- linux-yocto/6.6: update to v6.6.69
- ltng-modules: fix sched\_stat\_runtime changed in Linux 6.6.66
- migration-guides: add release notes for 5.0.6
- oeqa/ssh: allow to retrieve raw, unformatted output
- ovmf-native: remove .pyc files from install
- poky.conf: add new tested distros
- poky.conf: bump version for 5.0.7
- poky.yaml.in: add missing locales dependency
- poky.yaml.in: replace inkscape dependency by librsvg2-bin
- populate\_sdk\_ext: write\_local\_conf add shutil import
- pulseaudio: fix webrtc audio dependency
- python3-requests: upgrade to 2.32.3
- python3: Drop empty patch
- python3: add dependency on -compression to -core
- python3: upgrade to 3.12.7
- ref-manual: move runtime-testing section to the test-manual
- ref-manual: use standardized method across both ubuntu and debian for locale install
- ref-manual: SSTATE\_MIRRORS/SOURCE\_MIRROR\_URL: add instructions for mirror authentication
- reproducible-builds.rst: show how to build a single package
- rust-target-config: Fix TARGET\_C\_INT\_WIDTH with correct size
- rust: Revert "rust: Add new variable RUST\_ENABLE\_EXTRA\_TOOLS"
- rust: add reproducibility patch to eliminate host leakage
- rust: build the default set of tools
- rust: correctly link rust-snapshot into build/stage0
- rust: use rust-snapshot binaries only in rust-native
- sanity.bbclass: skip check\_userns for non-local uid
- scripts/install-buildtools: Update to 5.0.6
- system-requirements.rst: add dependencies for pdf builds
- system-requirements: add fedora 39 to supported distros
- system-requirements: update list of supported distros
- systemd: enable create-log-dirs
- test-manual/reproducible-builds: fix reproducible links

## Known Issues in Yocto-5.0.7

- N/A

## Contributors to Yocto-5.0.7

Thanks to the following people who contributed to this release:

- Aleksandar Nikolic
- Alexander Kanavin
- Alexis Lothoré
- Antonin Godard
- Archana Polampalli
- Bruce Ashfield
- Catalin Popescu
- Changqing Li
- Chen Qi
- Chris Laplante
- Divya Chellam
- Esben Haabendal
- Guénaél Muller
- Guðni Már Gilbert
- Harish Sadineni
- Hiago De Franco
- Hitendra Prajapati
- Jiaying Song
- Khem Raj
- Lee Chee Yang
- Mark Hatle
- Michael Opdenacker
- Mikko Rapeli
- Peter Marko
- Richard Purdie
- Robert Yang
- Ross Burton
- Soumya Sambu

- Steve Sakoman
- Sunil Dora
- Trevor Gamblin
- Xiangyu Chen
- Yash Shinde
- Zhang Peng
- Zahir Hussain

## Repositories / Downloads for Yocto-5.0.7

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.7`
- Git Revision: `7dad83c7e5e9637c0ff5d5712409611fd4a14946`
- Release Artefact: `poky-7dad83c7e5e9637c0ff5d5712409611fd4a14946`
- sha: `ae688031b19b88582bb4a76d0525e3704b981ad1d21eb38a0873cd01dd9a4652`
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.7/poky-7dad83c7e5e9637c0ff5d5712409611fd4a14946.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.7/poky-7dad83c7e5e9637c0ff5d5712409611fd4a14946.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.7`
- Git Revision: `62cb12967391db709315820d48853ffa4c6b4740`
- Release Artefact: `oecore-62cb12967391db709315820d48853ffa4c6b4740`
- sha: `bc45429df1805445b678f1b0ed6ce017edfac38c7226dce92ce393b3ef311f95`
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.7/oecore-62cb12967391db709315820d48853ffa4c6b4740.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.7/oecore-62cb12967391db709315820d48853ffa4c6b4740.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.7`
- Git Revision: `acbba477893ef87388effc4679b7f40ee49fc852`

- Release Artefact: meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852
- sha: 3b7c2f475dad5130bace652b150367f587d44b391218b1364a8bbc430b48c54c
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.7/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.7/meta-mingw-acbba477893ef87388effc4679b7f40ee49fc852.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0.7
- Git Revision: aa0e540fc31a1c26839efd2c7785a751ce24ebfb
- Release Artefact: bitbake-aa0e540fc31a1c26839efd2c7785a751ce24ebfb
- sha: 169b68ed7d5e55015b1c35a82d35efaa25c87cba4722c85e66514a15d31e1d28
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.7/bitbake-aa0e540fc31a1c26839efd2c7785a751ce24ebfb.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.7/bitbake-aa0e540fc31a1c26839efd2c7785a751ce24ebfb.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: scarthgap
- Tag: yocto-5.0.7
- Git Revision: bb9e018adcc10c642f87d0b95432783b5eb8057b

## 17.7.10 Release notes for Yocto-5.0.8 (Scarthgap)

### Security Fixes in Yocto-5.0.8

- binutils: Fix CVE-2025-0840
- curl: Ignore CVE-2025-0725
- elfutils: Fix CVE-2025-1352, CVE-2025-1365 and CVE-2025-1372
- ffmpeg: Fix CVE-2024-35365, CVE-2024-35369, CVE-2024-36613, CVE-2024-36616, CVE-2024-36617, CVE-2024-36618, CVE-2024-36619, CVE-2025-0518, CVE-2025-22919, CVE-2025-22921 and CVE-2025-25473
- glibc: Fix CVE-2025-0395
- gnutls: Fix CVE-2024-12243
- go: Fix CVE-2024-45336, CVE-2024-45341 and CVE-2025-22866
- gstreamer1.0-rtsp-server: Fix CVE-2024-44331
- libcap: Fix CVE-2025-1390

- libtasn1: Fix CVE-2024-12133
- libxml2: Fix CVE-2024-56171 and CVE-2025-24928
- linux-yocto/6.6: Fix CVE-2024-36476, CVE-2024-53179, CVE-2024-56582, CVE-2024-56703, CVE-2024-57801, CVE-2024-57802, CVE-2024-57841, CVE-2024-57882, CVE-2024-57887, CVE-2024-57890, CVE-2024-57892, CVE-2024-57895, CVE-2024-57896, CVE-2024-57900, CVE-2024-57901, CVE-2024-57902, CVE-2024-57906, CVE-2024-57907, CVE-2024-57908, CVE-2024-57910, CVE-2024-57911, CVE-2024-57912, CVE-2024-57913, CVE-2024-57916, CVE-2024-57922, CVE-2024-57925, CVE-2024-57926, CVE-2024-57933, CVE-2024-57938, CVE-2024-57939, CVE-2024-57940, CVE-2024-57949, CVE-2024-57951, CVE-2025-21631, CVE-2025-21636, CVE-2025-21637, CVE-2025-21638, CVE-2025-21639, CVE-2025-21640, CVE-2025-21642, CVE-2025-21652, CVE-2025-21658, CVE-2025-21665, CVE-2025-21666, CVE-2025-21667, CVE-2025-21669, CVE-2025-21670, CVE-2025-21671, CVE-2025-21673, CVE-2025-21674, CVE-2025-21675, CVE-2025-21676, CVE-2025-21680, CVE-2025-21681, CVE-2025-21683, CVE-2025-21684, CVE-2025-21687, CVE-2025-21689, CVE-2025-21690, CVE-2025-21692, CVE-2025-21694, CVE-2025-21697 and CVE-2025-21699
- openssh: Fix CVE-2025-26466
- openssl: Fix CVE-2024-9143, CVE-2024-12797 and CVE-2024-13176
- python3: Fix CVE-2024-12254 and CVE-2025-0938
- subversion: Ignore CVE-2024-45720
- u-boot: Fix CVE-2024-57254, CVE-2024-57255, CVE-2024-57256, CVE-2024-57257, CVE-2024-57258 and CVE-2024-57259
- vim: Fix CVE-2025-22134 and CVE-2025-24014
- xwayland: Fix CVE-2024-9632, CVE-2025-26594, CVE-2025-26595, CVE-2025-26596, CVE-2025-26597, CVE-2025-26598, CVE-2025-26599, CVE-2025-26600 and CVE-2025-26601

### Fixes in Yocto-5.0.8

- base-files: Drop /bin/sh dependency
- bind: upgrade to 9.18.33
- binutils: File name too long causing failure to open temporary head file in dlltool
- binutils: stable 2.42 branch update
- bitbake: bblayers/query: Fix using "removeprefix" string method
- bitbake: bitbake-diffsigs: fix handling when finding only a single sigfile
- bitbake: data\_smart.py: clear expand\_cache in \_setvar\_update\_overridevars
- bitbake: data\_smart.py: remove unnecessary ? from \_\_expand\_var\_regexp\_\_
- bitbake: data\_smart.py: simple clean up
- build-appliance-image: Update to scarthgap head revision
- ccache.conf: Add include\_file\_ctime to sloppiness
- cmake: apply parallel build settings to ptest tasks

- contributor-guide/submit-changes: add policy on AI generated code
- dev-manual/building: document the initramfs-framework recipe
- devtool: ide-sdk recommend *DEBUG\_BUILD*
- devtool: ide-sdk remove the plugin from eSDK installer
- devtool: ide-sdk sort cmake preset
- devtool: modify support debug-builds
- docs: Add favicon for the documentation html
- docs: Fix typo in standards.md
- docs: Remove all mention of core-image-lsb
- docs: vulnerabilities/classes: remove references to cve-check text format
- files: Amend overlayfs unit descriptions with path information
- files: overlayfs-create-dirs: Improve mount unit dependency
- glibc: stable 2.39 branch updates
- gnupg: upgrade to 2.4.5
- go: upgrade 1.22.12
- icu: remove host references in nativesdk to fix reproducibility
- libtasn1: upgrade to 4.20.0
- libxml2: upgrade to 2.12.10
- linux-yocto/6.6: upgrade to v6.6.75
- meta: Enable '-o pipefail' for the SDK installer
- migration-guides: add release notes for 4.0.24, 4.0.25 and 5.0.7
- oe-selftest: devtool ide-sdk use modify debug-build
- oeqa/sdk/context: fix for gtk3 test failure during do\_testsdk
- oeqa/selftest/rust: skip on all MIPS platforms
- openssl: upgrade to 3.2.4
- pkg-config-native: pick additional search paths from \$EXTRA\_NATIVE\_PKGCONFIG\_PATH
- poky.conf: add ubuntu2404 to *SANITY\_TESTED\_DISTROS*
- poky.conf: bump version for 5.0.8
- ppp: Revert lock path to /var/lock
- python3-setuptools-scm: respect GIT\_CEILING\_DIRECTORIES
- python3: upgrade to 3.12.9
- qemu: Do not define sched\_attr with glibc >= 2.41

- ref-manual/faq: add q&a on systemd as default
- ref-manual: Add missing variable *IMAGE\_ROOTFS\_MAXSIZE*
- ref-manual: don't refer to poky-lsb
- ref-manual: remove OE\_IMPORTS
- rust-common.bbclass: soft assignment for RUSTLIB path
- rust: fix for rust multilib sdk configuration
- rust: remove redundant cargo config file
- scripts/install-buildtools: Update to 5.0.7
- sdk-manual: extensible.rst: devtool ide-sdk improve
- sdk-manual: extensible.rst: update devtool ide-sdk
- selftest/rust: correctly form the PATH environment variable
- systemd: add libpcre2 as *RRECOMMENDS* if pcre2 is enabled
- systemd: upgrade to 255.17
- test-manual/ptest: link to common framework ptest classes
- tzcode-native: Fix compiler setting from 2023d version
- tzdata/tzcode-native: upgrade to 2025a
- u-boot: kernel-fitimage: Fix dependency loop if *UBOOT\_SIGN\_ENABLE* and UBOOT\_ENV enabled
- u-boot: kernel-fitimage: Restore FIT\_SIGN\_INDIVIDUAL="1" behavior
- uboot-config: fix devtool modify with kernel-fitimage
- vim: upgrade to 9.1.1043

### Known Issues in Yocto-5.0.8

- N/A

### Contributors to Yocto-5.0.8

Thanks to the following people who contributed to this release:

- Adrian Freihofer
- Aleksandar Nikolic
- Alessio Cascone
- Alexander Kanavin
- Alexis Cellier
- Antonin Godard
- Archana Polampalli
- Bruce Ashfield



- Chen Qi
- Deepesh Varatharajan
- Divya Chellam
- Enrico Jörns
- Esben Haabendal
- Etienne Cordonnier
- Fabio Berton
- Guðni Már Gilbert
- Harish Sadineni
- Hitendra Prajapati
- Hongxu Jia
- Jiaying Song
- Joerg Schmidt
- Johannes Schneider
- Khem Raj
- Lee Chee Yang
- Marek Vasut
- Marta Rybczynska
- Moritz Haase
- Oleksandr Hnatiuk
- Pedro Ferreira
- Peter Marko
- Poonam Jadhav
- Priyal Doshi
- Ross Burton
- Simon A. Eugster
- Steve Sakoman
- Vijay Anusuri
- Wang Mingyu
- Weisser, Pascal

## Repositories / Downloads for Yocto-5.0.8

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.8`
- Git Revision: `dc4827b3660bc1a03a2bc3b0672615b50e9137ff`
- Release Artefact: `poky-dc4827b3660bc1a03a2bc3b0672615b50e9137ff`
- sha: `ace7264e16e18ed02ef0ad2935fa10b5fad2c4de38b2356f4192b38ef2184504`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.8/poky-dc4827b3660bc1a03a2bc3b0672615b50e9137ff.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.8/poky-dc4827b3660bc1a03a2bc3b0672615b50e9137ff.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.8`
- Git Revision: `cd2b6080a4c0f2ed2c9939ec0b87763aef595048`
- Release Artefact: `oecore-cd2b6080a4c0f2ed2c9939ec0b87763aef595048`
- sha: `14c7cd5c62a96ceb9c2141164ea0f087fdbaed99ca3e9a722977a3f12d6381f6`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.8/oecore-cd2b6080a4c0f2ed2c9939ec0b87763aef595048.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.8/oecore-cd2b6080a4c0f2ed2c9939ec0b87763aef595048.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.8`
- Git Revision: `bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- Release Artefact: `meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- sha: `ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.8/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.8/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.8`

- Tag: `yocto-5.0.8`
- Git Revision: `7375d32e8c1af20c51abec4eb3b072b4ca58b239`
- Release Artefact: `bitbake-7375d32e8c1af20c51abec4eb3b072b4ca58b239`
- sha: `13dffbc162c5b6e2c95fa72936a430b9a542d52d81d502a5d0afc592fbf4a16b`
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.8/bitbake-7375d32e8c1af20c51abec4eb3b072b4ca58b239.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.8/bitbake-7375d32e8c1af20c51abec4eb3b072b4ca58b239.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.8`
- Git Revision: `7d3cce5b962ca9f73b29affceb7ebc6710627739`

## 17.7.11 Release notes for Yocto-5.0.9 (Scarthgap)

### Security Fixes in Yocto-5.0.9

- binutils: Fix CVE-2024-57360, CVE-2025-1176, CVE-2025-1178 and CVE-2025-1181
- expat: Fix CVE-2024-8176
- freetype: Fix CVE-2025-27363
- ghostscript: Fix CVE-2025-27830, CVE-2025-27831, CVE-2025-27832, CVE-2025-27833, CVE-2025-27833, CVE-2025-27834, CVE-2025-27835 and CVE-2025-27836
- go: fix CVE-2025-22870 and CVE-2025-22871
- grub: Fix CVE-2024-45781, CVE-2024-45774, CVE-2024-45775, CVE-2024-45776, CVE-2024-45777, CVE-2024-45778, CVE-2024-45779, CVE-2024-45780, CVE-2024-45782, CVE-2024-45783, CVE-2024-56737, CVE-2025-0622, CVE-2025-0624, CVE-2025-0677, CVE-2025-0678, CVE-2025-0684, CVE-2025-0685, CVE-2025-0686, CVE-2025-0689, CVE-2025-0690, CVE-2025-1118 and CVE-2025-1125
- libarchive: Fix CVE-2024-20696, CVE-2024-48957, CVE-2024-48958, CVE-2025-1632 and CVE-2025-25724
- libxslt: Fix CVE-2024-24855 and CVE-2024-55549
- linux-yocto/6.6: Fix CVE-2024-54458, CVE-2024-57834, CVE-2024-57973, CVE-2024-57978, CVE-2024-57979, CVE-2024-57980, CVE-2024-57981, CVE-2024-57984, CVE-2024-57996, CVE-2024-57997, CVE-2024-58002, CVE-2024-58005, CVE-2024-58007, CVE-2024-58010, CVE-2024-58011, CVE-2024-58013, CVE-2024-58017, CVE-2024-58020, CVE-2024-58034, CVE-2024-58052, CVE-2024-58055, CVE-2024-58058, CVE-2024-58063, CVE-2024-58068, CVE-2024-58069, CVE-2024-58070, CVE-2024-58071, CVE-2024-58076, CVE-2024-58080, CVE-2024-58083, CVE-2024-58088, CVE-2025-21700, CVE-2025-21703, CVE-2025-21707, CVE-2025-21711, CVE-2025-21715, CVE-2025-21716, CVE-2025-21718, CVE-2025-21726, CVE-2025-21727, CVE-2025-21731, CVE-2025-21735,

CVE-2025-21736, CVE-2025-21741, CVE-2025-21742, CVE-2025-21743, CVE-2025-21744, CVE-2025-21745, CVE-2025-21748, CVE-2025-21749, CVE-2025-21753, CVE-2025-21756, CVE-2025-21759, CVE-2025-21760, CVE-2025-21761, CVE-2025-21762, CVE-2025-21763, CVE-2025-21764, CVE-2025-21773, CVE-2025-21775, CVE-2025-21776, CVE-2025-21779, CVE-2025-21780, CVE-2025-21782, CVE-2025-21783, CVE-2025-21785, CVE-2025-21787, CVE-2025-21789, CVE-2025-21790, CVE-2025-21791, CVE-2025-21792, CVE-2025-21793, CVE-2025-21796, CVE-2025-21811, CVE-2025-21812, CVE-2025-21814, CVE-2025-21820, CVE-2025-21844, CVE-2025-21846, CVE-2025-21847, CVE-2025-21848, CVE-2025-21853, CVE-2025-21854, CVE-2025-21855, CVE-2025-21856, CVE-2025-21857, CVE-2025-21858, CVE-2025-21859, CVE-2025-21862, CVE-2025-21863, CVE-2025-21864, CVE-2025-21865, CVE-2025-21866, CVE-2025-21867, CVE-2025-21887, CVE-2025-21891, CVE-2025-21898, CVE-2025-21904, CVE-2025-21905, CVE-2025-21908, CVE-2025-21912, CVE-2025-21915, CVE-2025-21917, CVE-2025-21918, CVE-2025-21919, CVE-2025-21920, CVE-2025-21922, CVE-2025-21928, CVE-2025-21934, CVE-2025-21936, CVE-2025-21937, CVE-2025-21941, CVE-2025-21943, CVE-2025-21945, CVE-2025-21947, CVE-2025-21948, CVE-2025-21951, CVE-2025-21957, CVE-2025-21959, CVE-2025-21962, CVE-2025-21963, CVE-2025-21964, CVE-2025-21966, CVE-2025-21967, CVE-2025-21968, CVE-2025-21969, CVE-2025-21979, CVE-2025-21980, CVE-2025-21981, CVE-2025-21991 and CVE-2025-21993

- mpg123: Fix CVE-2024-10573
- ofono: Fix CVE-2024-7537
- openssh: Fix CVE-2025-26465
- puzzles: Ignore CVE-2024-13769, CVE-2024-13770 and CVE-2025-0837
- qemu: Ignore CVE-2023-1386
- ruby: Fix CVE-2025-27219 and CVE-2025-27220
- rust-cross-canadian: Ignore CVE-2024-43402
- vim: Fix CVE-2025-1215, CVE-2025-26603, CVE-2025-27423 and CVE-2025-29768
- xserver-xorg: Fix CVE-2025-26594, CVE-2025-26595, CVE-2025-26596, CVE-2025-26597, CVE-2025-26598, CVE-2025-26599, CVE-2025-26600 and CVE-2025-26601
- xz: Fix CVE-2025-31115

### Fixes in Yocto-5.0.9

- babeltrace2: extend to nativesdk
- babeltrace: extend to nativesdk
- bitbake: event/utls: Avoid deadlock from lock\_timeout() and recursive events
- bitbake: utls: Add signal blocking for lock\_timeout
- bitbake: utls: Print information about lock issue before exiting
- bitbake: utls: Tweak lock\_timeout logic
- build-appliance-image: Update to scarthgap head revision
- cve-check.bbclass: Mitigate symlink related error

- cve-update-nvd2-native: add workaround for json5 style list
- cve-update-nvd2-native: handle missing vulnStatus
- gcc: remove paths to sysroot from configargs.h and checksum-options for gcc-cross-canadian
- gcc: unify cleanup of include-fixed, apply to cross-canadian
- ghostscript: upgrade to 10.05.0
- grub: backport strlcpy function
- grub: drop obsolete CVE statuses
- icu: Adjust ICU\_DATA\_DIR path on big endian targets
- kernel-arch: add macro-prefix-map in KERNEL\_CC
- libarchive: upgrade to 3.7.9
- libxslt: upgrade to 1.1.43
- linux-yocto/6.6: update to v6.6.84
- mc: set ac\_cv\_path\_ZIP to avoid buildpaths QA issues
- mpg123: upgrade to 1.32.10
- nativesdk-libtool: sanitize the script, remove buildpaths
- openssl: rewrite ptest installation
- overview-manual/concepts: remove [PR](#) from the build dir list
- patch.py: set committer and commitemail for addNote
- poky.conf: bump version for 5.0.9
- vim: Upgrade to 9.1.1198
- xserver-xf86-config: add a configuration fragment to disable screen blanking
- xserver-xf86-config: remove obsolete configuration files
- xserver-xorg: upgrade to 21.1.16
- xz: upgrade to 5.4.7
- yocto-uninative: Update to 4.7 for glibc 2.41

### Known Issues in Yocto-5.0.9

- N/A

### Contributors to Yocto-5.0.9

Thanks to the following people who contributed to this release:

- Antonin Godard
- Archana Polampalli
- Ashish Sharma

- Bruce Ashfield
- Changqing Li
- Denys Dmytriienko
- Divya Chellam
- Hitendra Prajapati
- Madhu Marri
- Makarios Christakis
- Martin Jansa
- Michael Halstead
- Niko Mauno
- Oleksandr Hnatiuk
- Peter Marko
- Richard Purdie
- Ross Burton
- Sana Kazi
- Stefan Mueller-Klieser
- Steve Sakoman
- Vijay Anusuri
- Virendra Thakur
- Vishwas Udupa
- Wang Mingyu
- Zhang Peng

## Repositories / Downloads for Yocto-5.0.9

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.9`
- Git Revision: `bab0f9f62af9af580744948dd3240f648a99879a`
- Release Artefact: `poky-bab0f9f62af9af580744948dd3240f648a99879a`
- sha: `ee6811d9fb6c4913e19d6e3569f1edc8ccd793779b237520596506446a6b4531`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.9/poky-bab0f9f62af9af580744948dd3240f648a99879a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.9/poky-bab0f9f62af9af580744948dd3240f648a99879a.tar.bz2>

## openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.9`
- Git Revision: `04038ecd1edd6592b826665a2b787387bb7074fa`
- Release Artefact: `oecore-04038ecd1edd6592b826665a2b787387bb7074fa`
- sha: `6e201a4b486dfbdfcb7e96d83b962a205ec4764db6ad0e34bd623db18910eddb`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.9/oecore-04038ecd1edd6592b826665a2b787387bb7074fa.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.9/oecore-04038ecd1edd6592b826665a2b787387bb7074fa.tar.bz2>

## meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.9`
- Git Revision: `bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- Release Artefact: `meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- sha: `ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.9/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.9/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

## bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.8`
- Tag: `yocto-5.0.9`
- Git Revision: `696c2c1ef095f8b11c7d2eff36fae50f58c62e5e`
- Release Artefact: `bitbake-696c2c1ef095f8b11c7d2eff36fae50f58c62e5e`
- sha: `fc83f879cd6dd14b9b7eba0161fec23ecc191fed0fb00556ba729dceef6c145f`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.9/bitbake-696c2c1ef095f8b11c7d2eff36fae50f58c62e5e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.9/bitbake-696c2c1ef095f8b11c7d2eff36fae50f58c62e5e.tar.bz2>

## yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.9`

- Git Revision: 56db4fd81f6235428bef9e46a61c11ca0ba89733

## 17.7.12 Release notes for Yocto-5.0.10 (Scarthgap)

### Security Fixes in Yocto-5.0.10

- binutils: Fix CVE-2025-1153, CVE-2025-1179, CVE-2025-1180 and CVE-2025-1182
- connman: Fix CVE-2025-32366 and CVE-2025-32743
- curl: Fix CVE-2024-11053 and CVE-2025-0167
- elfutils: Fix CVE-2025-1371
- ffmpeg: Fix CVE-2024-7055, CVE-2024-32230, CVE-2024-35366, CVE-2024-36613, CVE-2024-36616, CVE-2024-36617 and CVE-2024-36619
- git: Fix CVE-2024-50349 and CVE-2024-52006
- glib-2.0: fix CVE-2025-3360 and CVE-2025-4373
- iputils: Fix CVE-2025-47268
- libpam: Fix CVE-2024-10041
- libsoup-2.4: Fix CVE-2024-52530, CVE-2024-52531, CVE-2024-52532, CVE-2025-32906, CVE-2025-32909, CVE-2025-32910, CVE-2025-32911, CVE-2025-32912, CVE-2025-32913, CVE-2025-32914 and CVE-2025-46420
- libsoup: Fix CVE-2025-4476, CVE-2025-32906, CVE-2025-32909, CVE-2025-32910, CVE-2025-32911, CVE-2025-32912, CVE-2025-32913, CVE-2025-32914 and CVE-2025-46420
- libxml2: Fix CVE-2025-32414 and CVE-2025-32415
- openssh: Fix CVE-2025-32728
- perl: Fix CVE-2024-56406
- ppp: Fix CVE-2024-58250
- python3-jinja2: Fix CVE-2024-56201, CVE-2024-56326 and CVE-2025-27516
- ruby: Fix CVE-2025-27221
- sqlite3: Fix CVE-2025-3277, CVE-2025-29087 and CVE-2025-29088

### Fixes in Yocto-5.0.10

- binutils: stable 2.42 branch updates
- bluez5: add missing tools to noinst-tools package
- bluez5: backport a patch to fix btmgmt -i
- bluez5: make media control a *PACKAGECONFIG* option
- build-appliance-image: Update to scarthgap head revision
- buildtools-tarball: Make buildtools respects host CA certificates
- buildtools-tarball: add envvars into *BB\_ENV\_PASSTHROUGH\_ADDITIONS*



- buildtools-tarball: move setting of envvars to respective envfile
- contributor-guide/submit-changes: encourage patch version changelogs
- cve-check.bbclass: Fix symlink handling also for text files
- cve-update-nvd2-native: Revert "cve-update-nvd2-native: Tweak to work better with NFS DL\_DIR"
- dev-manual/sbom.rst: fix wrong build outputs
- docs: Fix dead links that use the *DISTRO* macro
- docs: conf.py: tweak SearchEnglish to be hyphen-friendly
- docs:conf.py: define a manpage url
- ffmpeg: upgrade to 6.1.2
- git: upgrade to 2.44.3
- glibc-y2038-tests: remove glibc-y2038-tests\_2.39.bb recipe
- glibc: Add single-threaded fast path to rand()
- glibc: stable 2.39 branch updates
- initscripts: add function log\_success\_msg/log\_failure\_msg/log\_warning\_msg
- libatomic-ops: Update *GITHUB\_BASE\_URI*
- manuals: remove repeated word
- migration-guides: add release notes for 4.0.26, 5.0.8, 5.0.9
- module.bbclass: add KBUILD\_EXTRA\_SYMBOLS to install
- perl: upgrade to 5.38.4
- perlcross: upgrade to 1.6.2
- poky.conf: bump version for 5.0.10
- poky.yaml: introduce DISTRO\_LATEST\_TAG
- python3-jinja2: upgrade to 3.1.6
- ref-manual/release-process: update releases.svg
- ref-manual/variables.rst: HOST\_CC\_ARCH: fix wrong SDK reference
- ref-manual/variables.rst: WATCHDOG\_TIMEOUT: fix recipe name
- ref-manual/variables.rst: add manpage links for toolchain variables
- ref-manual/variables.rst: add missing documentation for BUILD\_\* variables
- ref-manual/variables.rst: document HOST\_\*\_ARCH variables
- ref-manual/variables.rst: document *INHIBIT\_DEFAULT\_RUST\_DEPS*
- ref-manual/variables.rst: document *INHIBIT\_UPDATERCD\_BBCLASS*
- ref-manual/variables.rst: document *SSTATE\_SKIP\_CREATION*

- ref-manual/variables.rst: document *WIC\_CREATE\_EXTRA\_ARGS*
- ref-manual/variables.rst: document autotools class related variables
- ref-manual/variables.rst: document missing *SDK\_\*\_ARCH* variables
- ref-manual/variables.rst: document the *IMAGE\_ROOTFS\_MAXSIZE* variable
- ref-manual/variables.rst: document the *INITRAMFS\_MAXSIZE* variable
- ref-manual/variables.rst: improve the *PKG* documentation
- ref-manual/variables.rst: update *ROOT\_HOME* documentation
- ref-manual: kernel-fitimage.bbclass does not use *SPL\_SIGN\_KEYNAME*
- scripts/install-buildtools: Update to 5.0.9
- sphinx-lint: missing space after literal
- sphinx-lint: trailing whitespace
- sphinx-lint: unbalanced inline literal markup
- systemd: Password agents shouldn't be optional
- systemd: upgrade to 255.18
- test-manual/intro: remove Buildbot version used
- tzdata/tzcode-native: upgrade 2025a -> 2025b
- u-boot: ensure keys are generated before assembling U-Boot FIT image
- util-linux: Add fix to isolate test fstab entries using *CUSTOM\_FSTAB*
- wic: bootimg-efi: Support + symbol in filenames

### Known Issues in Yocto-5.0.10

- There is an issue where the target libsoup-2.4 build may fail if apachectl is present on the build host. The issue only affects test binaries which aren't actually used. The issue can be fixed by disabling the tests or updating to more recent changes on the scarthgap branch which fix this.

### Contributors to Yocto-5.0.10

Thanks to the following people who contributed to this release:

- Adrian Freihofer
- Aleksandar Nikolic
- Alexander Kanavin
- Alon Bar-Lev
- Alper Ak
- Andrew Kreimer
- Antonin Godard

- Archana Polampalli
- Ashish Sharma
- Changqing Li
- Christos Gavros
- Deepesh Varatharajan
- Divya Chellam
- Divyanshu Rathore
- Enrico Jörns
- Etienne Cordonnier
- Guðni Már Gilbert
- Haixiao Yan
- Harish Sadineni
- Igor Opaniuk
- Jeroen Hofstee
- Lee Chee Yang
- Nguyen Dat Tho
- Niko Mauno
- Peter Marko
- Praveen Kumar
- Priyal Doshi
- Rogerio Guerra Borin
- Shubham Kulkarni
- Soumya Sambu
- Steve Sakoman
- Sunil Dora
- Trevor Woerner
- Vijay Anusuri
- Virendra Thakur
- Vyacheslav Yurkov
- Yi Zhao
- Yogita Urade
- rajmohan r

## Repositories / Downloads for Yocto-5.0.10

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: scarthgap
- Tag: yocto-5.0.10
- Git Revision: ac257900c33754957b2696529682029d997a8f28
- Release Artefact: poky-ac257900c33754957b2696529682029d997a8f28
- sha: ddca7e54b331e78214bea65b346320d4fbcddf4b51103bfbbd9fc3960f32cdc7
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.10/poky-ac257900c33754957b2696529682029d997a8f28.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.10/poky-ac257900c33754957b2696529682029d997a8f28.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: scarthgap
- Tag: yocto-5.0.10
- Git Revision: d5342ffc570d47a723b18297d75bd2f63c2088db
- Release Artefact: oecore-d5342ffc570d47a723b18297d75bd2f63c2088db
- sha: daa62094f2327f4b3fbcc485e8964d1b86a4722f58fb37e0d8e8e9885094a262
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.10/oecore-d5342ffc570d47a723b18297d75bd2f63c2088db.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.10/oecore-d5342ffc570d47a723b18297d75bd2f63c2088db.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: scarthgap
- Tag: yocto-5.0.10
- Git Revision: bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- Release Artefact: meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- sha: ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.10/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.10/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8

- Tag: `yocto-5.0.10`
- Git Revision: `696c2c1ef095f8b11c7d2eff36fae50f58c62e5e`
- Release Artefact: `bitbake-696c2c1ef095f8b11c7d2eff36fae50f58c62e5e`
- sha: `fc83f879cd6dd14b9b7eba0161fec23ecc191fed0fb00556ba729dceef6c145f`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.10/bitbake-696c2c1ef095f8b11c7d2eff36fae50f58c62e5e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.10/bitbake-696c2c1ef095f8b11c7d2eff36fae50f58c62e5e.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.10`
- Git Revision: `3996388e337377bedc113d072a51fe9d68dd40c6`

### 17.7.13 Release notes for Yocto-5.0.11 (Scarthgap)

#### Security Fixes in Yocto-5.0.11

- binutils: Fix CVE-2025-5244 and CVE-2025-5245
- busybox: Fix CVE-2022-48174
- coreutils: Fix CVE-2025-5278
- curl: Ignore CVE-2025-5025 if `PACKAGECONFIG` set with `openssl`
- ffmpeg: Fix CVE-2025-1373
- glibc: fix CVE-2025-4802 and CVE-2025-5702
- gnupg: Fix CVE-2025-30258
- go: Fix CVE-2025-4673
- go: Ignore CVE-2024-3566
- icu: Fix CVE-2025-5222
- kea: Fix CVE-2025-32801, CVE-2025-32802 and CVE-2025-32803
- libarchive: fix CVE-2025-5914, CVE-2025-5915, CVE-2025-5916, CVE-2025-5917 and CVE-2025-5918
- libsoup-2.4: Fix CVE-2025-2784, CVE-2025-4476, CVE-2025-4945, CVE-2025-4948, CVE-2025-4969, CVE-2025-32050, CVE-2025-32052, CVE-2025-32053, CVE-2025-32907 and CVE-2025-46421
- libsoup-3.4: Fix CVE-2025-2784, CVE-2025-4945, CVE-2025-4948, CVE-2025-4969, CVE-2025-32050, CVE-2025-32051, CVE-2025-32052, CVE-2025-32053, CVE-2025-32907, CVE-2025-32908 and CVE-2025-46421
- libxml2: Fix CVE-2025-6021

- linux-yocto-6.6: Fix [CVE-2025-21995](#), [CVE-2025-21996](#), [CVE-2025-21997](#), [CVE-2025-21999](#), [CVE-2025-22001](#), [CVE-2025-22003](#), [CVE-2025-22004](#), [CVE-2025-22005](#), [CVE-2025-22007](#), [CVE-2025-22009](#), [CVE-2025-22010](#), [CVE-2025-22014](#), [CVE-2025-22018](#), [CVE-2025-22020](#), [CVE-2025-22027](#), [CVE-2025-22033](#), [CVE-2025-22035](#), [CVE-2025-22038](#), [CVE-2025-22040](#), [CVE-2025-22041](#), [CVE-2025-22054](#), [CVE-2025-22056](#), [CVE-2025-22063](#), [CVE-2025-22066](#), [CVE-2025-22080](#), [CVE-2025-22081](#), [CVE-2025-22088](#), [CVE-2025-22097](#), [CVE-2025-23136](#), [CVE-2025-37785](#), [CVE-2025-37800](#), [CVE-2025-37801](#), [CVE-2025-37803](#), [CVE-2025-37805](#), [CVE-2025-37838](#), [CVE-2025-37893](#), [CVE-2025-38152](#), [CVE-2025-39728](#) and [CVE-2025-39735](#)
- net-tools: Fix [CVE-2025-46836](#)
- python3-setuptools: Fix [CVE-2025-47273](#)
- python3-requests: fix [CVE-2024-47081](#)
- python3-urllib3: Fix [CVE-2025-50181](#)
- python3: Fix [CVE 2024-12718](#) [CVE 2025-4138](#) [CVE 2025-4330](#) [CVE 2025-4435](#) [CVE-2025-4516](#) [CVE 2025-4517](#)
- screen: fix [CVE-2025-46802](#), [CVE-2025-46804](#) and [CVE-2025-46805](#)
- sudo: Fix [CVE-2025-32462](#)
- xwayland: Fix [CVE-2025-49175](#), [CVE-2025-49176](#), [CVE-2025-49177](#), [CVE-2025-49178](#), [CVE-2025-49179](#) and [CVE-2025-49180](#)

### Fixes in Yocto-5.0.11

- bitbake: ast: Change deferred inherits to happen per recipe
- bitbake: fetch2: Avoid deprecation warning
- bitbake: gcp.py: remove slow calls to gsutil stat
- bitbake: toaster/tests/buildtest: Switch to new CDN
- brief-yoctoprojectqs/ref-manual: Switch to new CDN
- bsp-guide: update kernel version example to 6.12
- bsp-guide: update all of section 1.8.2 to reflect current beaglebone conf file
- bsp-guide: update lonely "4.12" kernel reference to "6.12"
- build-appliance-image: Update to scarthgap head revision
- cmake: Correctly handle cost data of tests with arbitrary chars in name
- conf.py: improve SearchEnglish to handle terms with dots
- docs: Clean up explanation of minimum required version numbers
- docs: README: specify how to contribute instead of pointing at another file
- docs: conf.py: silence SyntaxWarning on js\_splitter\_code
- gcc: Upgrade to GCC 13.4
- ghostscript: upgrade to 10.05.1

- glibc: stable 2.39 branch updates (06a70769fd...)
- gnupg: update to 2.4.8
- gtk+: add missing libdrm dependency
- kea: upgrade to 2.4.2
- libpng: Add ptest
- libsoup-2.4: fix do\_compile failure
- linux-yocto/6.6: fix beaglebone ethernet
- linux-yocto/6.6: update to v6.6.96
- local.conf.sample: Switch to new CDN
- ltp: backport patch to fix compilation error for x86\_64
- migration-guides: add release notes for 4.0.27, 4.0.28, 5.0.10
- minicom: correct the *SRC\_URI*
- nfs-utils: don't use signals to shut down nfs server.
- overview-manual/concepts.rst: fix sayhello hardcoded bindir
- overview-manual: small number of pedantic cleanups
- package: export debugsources in *PKGDESTWORK* as json
- poky.conf: bump version for 5.0.11
- python3-requests: upgrade to 2.32.4
- python3: upgrade to 3.12.11
- ref-manual: clarify *KCONFIG\_MODE* default behaviour
- ref-manual: classes: nativesdk: move note to appropriate section
- ref-manual: classes: reword to clarify that native/nativesdk options are exclusive
- ref-manual: document *KERNEL\_SPLIT\_MODULES* variable
- scripts/install-buildtools: Update to 5.0.10
- spdx: add option to include only compiled sources
- sstatetests: Switch to new CDN
- systemd: Rename systemd\_v255.21 to systemd\_255.21
- systemd: upgrade to 255.21
- tcf-agent: correct the *SRC\_URI*
- testimage: get real os-release file
- tune-cortexr52: Remove aarch64 for ARM Cortex-R52
- uboot: Allow for customizing installed/deployed file names

## Known Issues in Yocto-5.0.11

- N/A

## Contributors to Yocto-5.0.11

Thanks to the following people who contributed to this release: - Aleksandar Nikolic - Andrew Fernandes - Antonin Godard - Archana Polampalli - Ashish Sharma - Bruce Ashfield - Carlos Sánchez de La Lama - Changqing Li - Chen Qi - Colin Pinnell McAllister - Daniel Turull - Deepesh Varatharajan - Divya Chellam - Dixit Parmar - Enrico Jörns - Etienne Cordonnier - Guocai He - Guðni Már Gilbert - Hitendra Prajapati - Jiaying Song - Lee Chee Yang - Moritz Haase - NeilBrown - Peter Marko - Poonam Jadhav - Praveen Kumar - Preeti Sachan - Quentin Schulz - Richard Purdie - Robert P. J. Day - Roland Kovacs - Ryan Eatmon - Sandeep Gundlupet Raju - Savvas Etairidis - Steve Sakoman - Victor Giraud - Vijay Anusuri - Virendra Thakur - Wang Mingyu - Yogita Urade

## Repositories / Downloads for Yocto-5.0.11

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.11](#)
- Git Revision: [ae2d52758fc2fcb0ed996aa234430464ebf4b310](#)
- Release Artefact: [poky-ae2d52758fc2fcb0ed996aa234430464ebf4b310](#)
- sha: [48dec434dd51e5c9c626abdbccc334da300fa2b4975137d526f5df6703e5a930e](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.11/poky-ae2d52758fc2fcb0ed996aa234430464ebf4b310.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.11/poky-ae2d52758fc2fcb0ed996aa234430464ebf4b310.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.11](#)
- Git Revision: [7a59dc5ee6edd9596e87c2fbcd1f2594c06b3d1b](#)
- Release Artefact: [oecore-7a59dc5ee6edd9596e87c2fbcd1f2594c06b3d1b](#)
- sha: [fb50992a28298915fe195e327628d6d5872fd2dbc74189c2d840178cd860bb2e](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.11/oecore-7a59dc5ee6edd9596e87c2fbcd1f2594c06b3d1b.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.11/oecore-7a59dc5ee6edd9596e87c2fbcd1f2594c06b3d1b.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [scarthgap](#)



- Tag: `yocto-5.0.11`
- Git Revision: `bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- Release Artefact: `meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- sha: `ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.11/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.11/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.8`
- Tag: `yocto-5.0.11`
- Git Revision: `139f61fe9eec221745184a14b3618d2dfa650b91`
- Release Artefact: `bitbake-139f61fe9eec221745184a14b3618d2dfa650b91`
- sha: `86669d4220c50d35c0703f151571954ad9c6285cc91a870afbb878d2e555d2ca`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.11/bitbake-139f61fe9eec221745184a14b3618d2dfa650b91.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.11/bitbake-139f61fe9eec221745184a14b3618d2dfa650b91.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `scarthgap`
- Tag: `yocto-5.0.11`
- Git Revision: `50e5c0d85d3775ac1294bdcd7f11deaa382c9d08`

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.11`
- Git Revision: `3f88cb85cca8f9128cfaab36882c4563457b03d9`

## 17.7.14 Release notes for Yocto-5.0.12 (Scarthgap)

### Security Fixes in Yocto-5.0.12

- avahi: Fix CVE-2024-52615
- binutils: Fix CVE-2025-7545 and CVE-2025-7546
- busybox: Fix CVE-2023-39810
- dropbear: Fix CVE-2025-47203

- gdk-pixbuf: Fix [CVE-2025-7345](#)
- git: Fix [CVE-2025-27613](#), [CVE-2025-27614](#), [CVE-2025-46334](#), [CVE-2025-46835](#), [CVE-2025-48384](#), [CVE-2025-48385](#) and [CVE-2025-48386](#)
- glib-2.0: Ignore [CVE-2025-4056](#)
- glibc: Fix [CVE-2025-8058](#)
- gnutls: Fix [CVE-2025-6395](#), [CVE-2025-32988](#), [CVE-2025-32989](#) and [CVE-2025-32990](#)
- go: Ignore [CVE-2025-0913](#)
- gstreamer1.0-plugins-base: Fix [CVE-2025-47806](#) and [CVE-2025-47808](#)
- gstreamer1.0-plugins-good: Fix [CVE-2025-47183](#) and [CVE-2025-47219](#)
- iputils: Fix [CVE-2025-48964](#)
- libpam: Fix [CVE-2025-6020](#)
- libxml2: Fix [CVE-2025-6170](#), [CVE-2025-49794](#), [CVE-2025-49795](#) and [CVE-2025-49796](#)
- libxml2: Ignore [CVE-2025-8732](#)
- ncurses: Fix [CVE-2025-6141](#)
- openssl: Fix [CVE-2024-41996](#) and [CVE-2025-27587](#)
- python3: Fix [CVE-2025-8194](#)
- sqlite3: Fix [CVE-2025-6965](#)
- sudo: Fix [CVE-2025-32463](#)
- xserver-xorg: Fix [CVE-2022-49737](#), [CVE-2025-49175](#), [CVE-2025-49176](#), [CVE-2025-49177](#), [CVE-2025-49178](#), [CVE-2025-49179](#), [CVE-2025-49180](#) and [CVE-2025-49176](#)
- xz: Ignore [CVE-2024-47611](#)

### Fixes in Yocto-5.0.12

- bash: Stick to C17 std
- bash: use `-std=gnu17` also for native *CFLAGS*
- binutils: stable 2.42 branch updates
- bitbake: bitbake: runqueue: Verify mcdepends are valid
- bitbake: test/fetch: Switch u-boot based test to use our own mirror
- bitbake: utils: Optimise signal/sigmask performance
- build-appliance-image: Update to scarthgap head revision
- cairo: fix build with gcc-15 on host
- cmake: Add *PACKAGECONFIG* option for debugger support
- cve-check: Add missing call to `exit_if_errors`
- dev-manual/start.rst: added missing command in Optimize your VHDX file using DiskPart

- e2fsprogs: Fix build failure with gcc 15
- git: Upgrade to 2.44.4
- glibc: stable 2.39 branch updates
- gnutils: patch read buffer overrun in the "pre\_shared\_key" extension
- gnutils: patch reject zero-length version in certificate request
- go-helloworld: fix license
- kea: set correct permissions for /var/run/kea
- linux-libc-headers: Fix invalid conversion in cn\_proc.h
- migration-guides: add release notes for 5.0.11
- mtools: upgrade to 4.0.49
- oe-debuginfod: add option for data storage
- orc: set *CVE\_PRODUCT*
- overview-manual/yp-intro.rst: fix broken link to article
- parted: Fix build with GCC 15
- poky.conf: bump version for 5.0.12
- python3: update CVE product
- ref-manual/classes.rst: document the testexport class
- ref-manual/system-requirements.rst: update supported distributions
- ref-manual/variables.rst: document *SPL\_DTB\_BINARY FIT\_CONF\_PREFIX* variable
- scripts/install-buildtools: Update to 5.0.11
- sudo: upgrade to 1.9.17p1
- timedated: wait for jobs before SetNTP response
- variables.rst: remove references to obsolete tar packaging
- xserver-xorg: upgrade to 21.1.18

### Known Issues in Yocto-5.0.12

- N/A

### Contributors to Yocto-5.0.12

Thanks to the following people who contributed to this release: - Aleksandar Nikolic - Alexander Kanavin - Antonin Godard - Archana Polampalli - Daniel Turull - Deepesh Varatharajan - Erik Lindsten - Fabio Berton - Hitendra Prajapati - Jinfeng Wang - Joe Slater - Khem Raj - Lee Chee Yang - Marco Cavallini - Mark Hatle - Martin Jansa - Michal Seben - Nikhil R - Peter Marko - Philip Lorenz - Praveen Kumar - Quentin Schulz - Richard Purdie - Robert P. J. Day - Roland Kovacs - Steve Sakoman - Vijay Anusuri - Wang Mingyu - Yash Shinde - Yi Zhao - Zhang Peng

## Repositories / Downloads for Yocto-5.0.12

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: scarthgap
- Tag: yocto-5.0.12
- Git Revision: ec220ae083dba35c279192b2249ad03fe238446e
- Release Artefact: poky-ec220ae083dba35c279192b2249ad03fe238446e
- sha: a5f8c2ad491c59d0bdfb85f46a136b0ee66cfdd4359ab1ab9dac2430d0a52c17
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.12/poky-ec220ae083dba35c279192b2249ad03fe238446e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.12/poky-ec220ae083dba35c279192b2249ad03fe238446e.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: scarthgap
- Tag: yocto-5.0.12
- Git Revision: 93c7489d843a0e46fe4fc685b356d0ae885300d7
- Release Artefact: oecore-93c7489d843a0e46fe4fc685b356d0ae885300d7
- sha: 49695592179cd777eee337d922aae354dad4ab503628f0344b1b53329900c4d9
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.12/oecore-93c7489d843a0e46fe4fc685b356d0ae885300d7.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.12/oecore-93c7489d843a0e46fe4fc685b356d0ae885300d7.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: scarthgap
- Tag: yocto-5.0.12
- Git Revision: bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- Release Artefact: meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- sha: ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.12/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.12/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8

- Tag: `yocto-5.0.12`
- Git Revision: `982645110a19ebb94d519926a4e14c8a2a205cfd`
- Release Artefact: `bitbake-982645110a19ebb94d519926a4e14c8a2a205cfd`
- sha: `f8d777d322b8f05372d7ce75c67df2db2b7de3f64d5b7769b8051c507161245d`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.12/bitbake-982645110a19ebb94d519926a4e14c8a2a205cfd.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.12/bitbake-982645110a19ebb94d519926a4e14c8a2a205cfd.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `scarthgap`
- Tag: `yocto-5.0.12`
- Git Revision: `82602cda1a89644d1acbe230a81c93e3fb5031c8`

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.12`
- Git Revision: `dd665216fa578a1f2f268790d708c6a5d2912ecf`

## 17.7.15 Release notes for Yocto-5.0.13 (Scarthgap)

### Security Fixes in Yocto-5.0.13

- busybox: Fix CVE-2025-46394
- cups: Fix CVE-2025-58060 and CVE-2025-58364
- curl: Fix CVE-2025-9086
- dpkg: Fix CVE-2025-6297
- expat: follow-up Fix CVE-2024-8176
- ffmpeg: Fix CVE-2025-1594
- ffmpeg: Ignore CVE-2023-49502, CVE-2023-50007, CVE-2023-50008, CVE-2023-50009, CVE-2023-50010, CVE-2024-31578, CVE-2024-31582 and CVE-2024-31585
- ghostscript: Fix CVE-2025-59798, CVE-2025-59799 and CVE-2025-59800
- glib-2.0: Fix CVE-2025-6052 and CVE-2025-7039
- go-binary-native: Ignore CVE-2025-0913
- go: Fix CVE-2025-4674, CVE-2025-47906 and CVE-2025-47907
- grub2: Fix CVE-2024-56738
- grub2: Ignore CVE-2024-2312

- gstreamer1.0-plugins-bad: Fix [CVE-2025-3887](#)
- gstreamer1.0-plugins-base: Fix [CVE-2025-47807](#)
- gstreamer1.0-plugins-base: Ignore [CVE-2025-47806](#) and [CVE-2025-47808](#)
- gstreamer1.0-plugins-good: Ignore [CVE-2025-47183](#) and [CVE-2025-47219](#)
- gstreamer1.0: Ignore [CVE-2025-2759](#)
- libpam: Fix [CVE-2024-10963](#)
- libxslt: Fix [CVE-2025-7424](#)
- openssl: Fix [CVE-2025-9230](#), [CVE-2025-9231](#) and [CVE-2025-9232](#)
- pulseaudio: Ignore [CVE-2024-11586](#)
- qemu: Ignore [CVE-2024-7730](#)
- tiff: Fix [CVE-2025-9900](#)
- tiff: Ignore [CVE-2024-13978](#), [CVE-2025-8176](#), [CVE-2025-8177](#), [CVE-2025-8534](#) and [CVE-2025-8851](#)
- vim: Fix [CVE-2025-9389](#)
- wpa-suplicant: Fix [CVE-2022-37660](#)

### Fixes in Yocto-5.0.13

- binutils: fix build with gcc-15
- bitbake: Use a "fork" multiprocessing context
- bitbake: bitbake: Bump version to 2.8.1
- build-appliance-image: Update to scarthgap head revision
- buildtools-tarball: fix unbound variable issues under 'set -u'
- cmake: fix build with gcc-15 on host
- conf/bitbake.conf: use gnu mirror instead of main server
- contributor-guide: submit-changes: align [CC](#) tag description
- contributor-guide: submit-changes: clarify example with Yocto bug ID
- contributor-guide: submit-changes: fix improper bold string
- contributor-guide: submit-changes: make "Crediting contributors" part of "Commit your changes"
- contributor-guide: submit-changes: make the Cc tag follow kernel guidelines
- contributor-guide: submit-changes: number instruction list in commit your changes
- contributor-guide: submit-changes: reword commit message instructions
- cpio: Pin to use C17 std
- cups: upgrade to 2.4.11
- curl: update [CVE\\_STATUS](#) for [CVE-2025-5025](#)

- dbus-glib: fix build with gcc-15
- default-distrovars.inc: Fix CONNECTIVITY\_CHECK\_URI redirect issue
- dev-manual/building.rst: add note about externalsrc variables absolute paths
- dev-manual/security-subjects.rst: update mailing lists
- elfutils: fix build with gcc-15
- examples: genl: fix wrong attribute size
- expect: Fix build with GCC 15
- expect: Revert "expect-native: fix do\_compile failure with gcc-14"
- expect: cleanup do\_install
- expect: don't run aclocal in do\_configure
- expect: fix native build with GCC 15
- expect: update code for Tcl channel implementation
- ffmpeg: upgrade to 6.1.3
- gdbm: Use C11 standard
- git: fix build with gcc-15 on host
- gmp: Fix build with GCC15/C23
- gmp: Fix build with older gcc versions
- kernel-dev/common.rst: fix the in-tree defconfig description
- lib/oe/utis: use multiprocessing from bb
- libarchive: patch regression of patch for [CVE-2025-5918](#)
- libgpg-error: fix build with gcc-15
- libtirpc: Fix build with gcc-15/C23
- license.py: avoid deprecated ast.Str
- llvm: fix build with gcc-15
- llvm: update to 18.1.8
- m4: Stick to C17 standard
- migration-guides: add release notes for 4.0.29 5.0.12
- ncurses: Pin to C17 standard
- oeqa/sdk/cases/buildcpio.py: use gnu mirror instead of main server
- openssl: upgrade to 3.2.6
- p11-kit: backport fix for handle [USE\\_NLS](#) from master
- pkgconfig: fix build with gcc-15

- poky.conf: bump version for 5.0.13
- pulseaudio: Add audio group explicitly
- ref-manual/structure: document the auto.conf file
- ref-manual/variables.rst: expand *IMAGE\_OVERHEAD\_FACTOR* glossary entry
- ref-manual/variables.rst: fix the description of *KBUILD\_DEFCONFIG STAGING\_DIR*
- rpm: keep leading "/" from sed operation
- ruby-ptest: some ptest fixes
- runqemu: fix special characters bug
- rust-llvm: fix build with gcc-15
- sanity.conf: Update minimum bitbake version to 2.8.1
- scripts/install-buildtools: Update to 5.0.12
- sdk: The main in the C example should return an int
- selftest/cases/meta\_ide.py: use use gnu mirror instead of main server
- shared-mime-info: Handle *USE\_NLS*
- sudo: remove devtool FIXME comment
- systemd: backport fix for handle *USE\_NLS* from master
- systemtap: Fix task\_work\_cancel build
- test-manual/yocto-project-compatible.rst: fix a typo
- test-manual: update runtime-testing Exporting Tests section
- unifdef: Don't use C23 constexpr keyword
- unzip: Fix build with GCC-15
- util-linux: use \${B} instead of \${WORKDIR}/build, to fix building under devtool
- vim: upgrade to 9.1.1683
- yocto-uninative: Update to 4.9 for glibc 2.42 GCC 15.1

### Known Issues in Yocto-5.0.13

- N/A

### Contributors to Yocto-5.0.13

Thanks to the following people who contributed to this release: - Adam Blank - Adrian Freihofer - Aleksandar Nikolic - Antonin Godard - Archana Polampalli - AshishKumar Mishra - Barne Carstensen - Chris Laplante - Deepak Rathore - Divya Chellam - Gyorgy Sarvari - Haixiao Yan - Hitendra Prajapati - Hongxu Jia - Jan Vermaete - Jiaying Song - Jinfeng Wang - Joao Marcos Costa - Joshua Watt - Khem Raj - Kyungjik Min - Lee Chee Yang - Libo Chen - Martin Jansa - Michael Halstead - Nitin Wankhade - Peter Marko - Philip Lorenz - Praveen Kumar - Quentin Schulz - Ross Burton - Stanislav Vovk - Steve Sakoman - Talel BELHAJ SALEM - Vijay Anusuri - Vrushti Dabhi - Yogita Urade



## Repositories / Downloads for Yocto-5.0.13

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `scarthgap`
- Tag: `yocto-5.0.13`
- Git Revision: `6f086fd3d9dbbb0c80f6c3e89b8df4fed422e79a`
- Release Artefact: `yocto-docs-6f086fd3d9dbbb0c80f6c3e89b8df4fed422e79a`
- sha: `454601d8b6034268212f74ca689ed360b08f7a4c7de5df726aa3706586ca4351`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.13/yocto-docs-6f086fd3d9dbbb0c80f6c3e89b8df4fed422e79a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.13/yocto-docs-6f086fd3d9dbbb0c80f6c3e89b8df4fed422e79a.tar.bz2>

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.13`
- Git Revision: `f16cffd030d21d12dd57bb95cfc310bda41f8a1f`
- Release Artefact: `poky-f16cffd030d21d12dd57bb95cfc310bda41f8a1f`
- sha: `1367e43907f5ffa725f3afb019cd7ca07de21f13e5e73a1f5d1808989ae6ed2a`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.13/poky-f16cffd030d21d12dd57bb95cfc310bda41f8a1f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.13/poky-f16cffd030d21d12dd57bb95cfc310bda41f8a1f.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.13`
- Git Revision: `7af6b75221d5703ba5bf43c7cd9f1e7a2e0ed20b`
- Release Artefact: `oecore-7af6b75221d5703ba5bf43c7cd9f1e7a2e0ed20b`
- sha: `4dcf636ec4a7b38b47a24e9cb3345b385bc126bb19620bf6af773bf292fef6b2`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.13/oecore-7af6b75221d5703ba5bf43c7cd9f1e7a2e0ed20b.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.13/oecore-7af6b75221d5703ba5bf43c7cd9f1e7a2e0ed20b.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `scarthgap`

- Tag: yocto-5.0.13
- Git Revision: 3ff7ca786732390cd56ae92ff4a43aba46a1bf2e
- Release Artefact: meta-yocto-3ff7ca786732390cd56ae92ff4a43aba46a1bf2e
- sha: 8efbaeab49dc3e1c4b67ff8d5801df1b05204c2255d18cff9a6857769ae33b23
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.13/meta-yocto-3ff7ca786732390cd56ae92ff4a43aba46a1bf2e.tar.bz2>   <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.13/meta-yocto-3ff7ca786732390cd56ae92ff4a43aba46a1bf2e.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: scarthgap
- Tag: yocto-5.0.13
- Git Revision: bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- Release Artefact: meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- sha: ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.13/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>   <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.13/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0.13
- Git Revision: 1c9ec1ffde75809de34c10d3ec2b40d84d258cb4
- Release Artefact: bitbake-1c9ec1ffde75809de34c10d3ec2b40d84d258cb4
- sha: 98bf54fa3abe237b73a93b1e33842a429209371fca6e409c258a441987879d16
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.13/bitbake-1c9ec1ffde75809de34c10d3ec2b40d84d258cb4.tar.bz2>   <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.13/bitbake-1c9ec1ffde75809de34c10d3ec2b40d84d258cb4.tar.bz2>

## 17.7.16 Release notes for Yocto-5.0.14 (Scarthgap)

### Security Fixes in Yocto-5.0.14

- bind: Fix CVE-2025-8677, CVE-2025-40778 and CVE-2025-40780
- binutils: Fix CVE-2025-8225, CVE-2025-11081, CVE-2025-11082, CVE-2025-11083, CVE-2025-11412, CVE-2025-11413 and CVE-2025-11414
- cmake: fix CVE-2025-9301
- curl: Ignore CVE-2025-10966

- elfutils: Fix [CVE-2025-1376](#) and [CVE-2025-1377](#)
- expat: Fix [CVE-2025-59375](#)
- glib-networking: Fix [CVE-2025-60018](#) and [CVE-2025-60019](#)
- gnupg: Ignore [CVE-2025-30258](#)
- go: Fix [CVE-2025-47912](#), [CVE-2025-58185](#), [CVE-2025-58187](#), [CVE-2025-58188](#), [CVE-2025-58189](#), [CVE-2025-61723](#) and [CVE-2025-61724](#)
- libpam: Ignore [CVE-2025-6018](#)
- lz4: Fix [CVE-2025-62813](#)
- openssh: Fix [CVE-2025-61984](#) and [CVE-2025-61985](#)
- python3: Fix [CVE-2025-59375](#)
- python3-xmltodict: Fix [CVE-2025-9375](#)
- qemu: Fix [CVE-2024-8354](#)
- tiff: Ignore [CVE-2025-8961](#)
- u-boot: Fix [CVE-2024-42040](#)
- wpa-suplicant: Fix [CVE-2025-24912](#)

#### Fixes in Yocto-5.0.14

- bind: upgrade to 9.18.41
- bitbake: bb/fetch2/\_\_init\_\_.py: remove a DeprecationWarning in uri\_replace()
- bitbake: fetch2/wget: Keep query parameters in URL during checkstatus
- build-appliance-image: Update to scarthgap head revision
- ca-certificates: Add comment for provenance of [SRCREV](#)
- ca-certificates: fix on-target postinstall script
- ca-certificates: get sources from debian tarballs
- ca-certificates: submit sysroot patch upstream, drop default-sysroot.patch
- ca-certificates: upgrade to 20250419
- classes/create-spdx-2.2: align DEPLOY\_DIR\_SPDX with SPDX\_VERSION layout
- classes/create-spdx-2.2: Handle empty packages
- classes-global/license: Move functions to library code
- classes-global/staging: Exclude do\_create\_spdx from automatic sysroot extension
- classes-recipe/baremetal-image: Add image file manifest
- classes-recipe/image: Add image file manifest
- curl: only set CA bundle in target build

- dev-manual, test-manual: Update autobuilder output links
- flex: fix build with gcc-15 on host
- glibc: stable 2.39 branch updates
- gstreamer1.0-plugins-bad: fix buffer allocation fail for v4l2codecs
- icu: Backport patch to fix build issues with long paths (>512 chars)
- iptables: remove /etc/ethertypes
- lib/license: Move package license skip to library
- lib: oe: license: Add missing import
- lib: oeqa: spdx: Add tests for extra options
- linux-yocto/6.6: update to v6.6.111
- meta: backport *SPDX* 3.0 fixes and tasks from upstream version Walnascar
- migration-guides: add release notes for 4.0.30
- oe-build-perf-report: relax metadata matching rules
- oe-core: Remove empty file
- oeqa/runtime/ping: don't bother trying to ping localhost
- oeqa/selftest: Add *SPDX* 3.0 include source case for work-share
- oeqa/selftest/devtool: Update after upstream repo changes
- oeqa: spdx: Add tar test for *SPDX* 2.2
- overview-manual/yp-intro.rst: update on-target packaging info
- perf: add arm64 source files for unistd\_64.h
- poky.conf: bump version for 5.0.14
- python3: upgrade to 3.12.12
- ref-manual/classes.rst: document the relative\_symlinks class
- ref-manual/classes.rst: extend the uninative class documentation
- ref-manual/classes.rst: gettext: extend the documentation of the class
- ref-manual/variables.rst: document *CCACHE\_DISABLE* *CHECKSUM* *UNINATIVE\_URL* *REQUIRED\_COMBINED\_FEATURES* *REQUIRED\_IMAGE\_FEATURES* *REQUIRED\_MACHINE\_FEATURES* *USE\_NLS* variable
- ref-manual/variables.rst: fix *LAYERDEPENDS* description
- selftest: spdx: Add *SPDX* 3.0 test cases
- selftest/spdx: Fix for *SPDX\_VERSION* addition
- spdx 3.0: Rework how *SPDX* aliases are linked
- spdx30\_tasks: adapt CVE handling to new cve-check API

- sdx30\_tasks: fix FetchData attribute in add\_download\_files
- util-linux: fix pointer usage in hwclock param handling
- vulnerabilities: update nvdcve file name
- webkitgtk: upgrade to 2.44.4
- wireless-regdb: upgrade to 2025.10.07
- xf86-video-intel: correct [SRC\\_URI](#) as freedesktop anongit is down

### Known Issues in Yocto-5.0.14

- N/A

### Contributors to Yocto-5.0.14

Thanks to the following people who contributed to this release: - Alexander Kanavin - Anders Heimer - Ankur Tyagi - Antonin Godard - Archana Polampalli - Bastian Krause - Bin Lan - Bruce Ashfield - Carlos Alberto Lopez Perez - Daniel Semkowicz - David Nyström - Deepesh Varatharajan - Gyorgy Sarvari - Hongxu Jia - Joshua Watt - João Marcos Costa - Kamel Bouhara (Schneider Electric) - Lee Chee Yang - Martin Jansa - Matthias Schiffer - Michael Haener - Paul Barker - Peter Marko - Philippe-Alexandre Mathieu - Praveen Kumar - Rajeshkumar Ramasamy - Rasmus Villemoes - Richard Purdie - Robert P. J. Day - Saravanan - Soumya Sambu - Steve Sakoman - Theodore A. Roth - Wang Mingyu - Yannic Moog - Yash Shinde - Yogita Urade

### Repositories / Downloads for Yocto-5.0.14

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.14](#)
- Git Revision: [a8687e4bb2e822670b6ad110613a12fa02943d3d](#)
- Release Artefact: [yocto-docs-a8687e4bb2e822670b6ad110613a12fa02943d3d](#)
- sha: [72a51b6049a59f773720d9b0aa94f090222a41aeb22d65c5f4211c78418fb6fa](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.14/yocto-docs-a8687e4bb2e822670b6ad110613a12fa02943d3d.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.14/yocto-docs-a8687e4bb2e822670b6ad110613a12fa02943d3d.tar.bz2>

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.14](#)
- Git Revision: [7e8674996b0164b07e56bc066d0fba790e627061](#)
- Release Artefact: [poky-7e8674996b0164b07e56bc066d0fba790e627061](#)

- sha: 071e189ebccfad99d4d79ea9021475296fa642611828249f0963b019f842a021
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.14/poky-7e8674996b0164b07e56bc066d0fba790e627061.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.14/poky-7e8674996b0164b07e56bc066d0fba790e627061.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: scarthgap
- Tag: yocto-5.0.14
- Git Revision: 471adaa5f77fa3b974eab60a2ded48e360042828
- Release Artefact: oecore-471adaa5f77fa3b974eab60a2ded48e360042828
- sha: 4dfad047a68aea2293845cdb4a86911bb3b1b0444a63f51b4e5a2448018d6a5e
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.14/oecore-471adaa5f77fa3b974eab60a2ded48e360042828.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.14/oecore-471adaa5f77fa3b974eab60a2ded48e360042828.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: scarthgap
- Tag: yocto-5.0.14
- Git Revision: bf6aea52c4009e08f26565c33ce432eec7cfb090
- Release Artefact: meta-yocto-bf6aea52c4009e08f26565c33ce432eec7cfb090
- sha: 92c9da1027efaf945d80bcd44984d5f8e7606c7ded485b57c0c8f47c9fa1302d
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.14/meta-yocto-bf6aea52c4009e08f26565c33ce432eec7cfb090.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.14/meta-yocto-bf6aea52c4009e08f26565c33ce432eec7cfb090.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: scarthgap
- Tag: yocto-5.0.14
- Git Revision: bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- Release Artefact: meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f
- sha: ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.14/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.14/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0.14
- Git Revision: 8dcf084522b9c66a6639b5f117f554fde9b6b45a
- Release Artefact: bitbake-8dcf084522b9c66a6639b5f117f554fde9b6b45a
- sha: 766eda21f2a914276d2723b1d8248be11507f954aef8fc5bb1767f3cb65688dd
- Download                Locations:                <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.14/bitbake-8dcf084522b9c66a6639b5f117f554fde9b6b45a.tar.bz2>                <https://mirrors.kernel.org/yocto/yocto/yocto-5.0.14/bitbake-8dcf084522b9c66a6639b5f117f554fde9b6b45a.tar.bz2>

### 17.7.17 Release notes for Yocto-5.0.15 (Scarthgap)

Users of Alma 9, Rocky 9 and Centos Stream 9 rolling releases have seen obtuse failures in the execution of tar in various tasks after recent host distro updates. These newer versions of tar contain a CVE fix which uses a new glibc call/syscall (openat2). The fix is to update to a newer pseudo version which handles this syscall. This is not included in this stable release but we aim to include it in the next one.

#### Security Fixes in Yocto-5.0.15

- binutils: Fix CVE-2025-11494, CVE-2025-11839 and CVE-2025-11840
- cmake-native: Fix CVE-2025-9301
- cups: Fix CVE-2025-58436 and CVE-2025-61915
- gnutls: Fix CVE-2025-9820
- go: Fix CVE-2025-61727 and CVE-2025-61729
- go: Update CVE-2025-58187 patches
- grub: Fix CVE-2025-54770, CVE-2025-61661, CVE-2025-61662, CVE-2025-61663 and CVE-2025-61664
- libarchive: Fix CVE-2025-60753
- libarchive: Fix 2 security issue (<https://github.com/libarchive/libarchive/pull/2753> and <https://github.com/libarchive/libarchive/pull/2768>)
- libmicrohttpd: Ignore CVE-2025-59777 and CVE-2025-62689
- libpng: Fix CVE-2025-64505, CVE-2025-64506, CVE-2025-64720, CVE-2025-65018 and CVE-2025-66293
- libsoup: Fix CVE-2025-12105
- libssh2: Fix CVE-2023-48795
- libxml2: Fix CVE-2025-7425
- libxslt: Fix CVE-2025-11731
- musl: Fix CVE-2025-26519

- python3-urllib3: Fix [CVE-2025-66418](#) and [CVE-2025-66471](#)
- python3: Fix [CVE-2025-6075](#)
- qemu: Fix [CVE-2025-12464](#)
- rsync: Fix [CVE-2025-10158](#)
- ruby: Fix [CVE-2025-24294](#), [CVE-2025-25186](#) and [CVE-2025-61594](#)
- sqlite3: Fix [CVE-2025-7709](#)
- xserver-xorg: Fix [CVE-2025-62229](#), [CVE-2025-62230](#) and [CVE-2025-62231](#)
- xwayland: Fix [CVE-2025-62229](#), [CVE-2025-62230](#) and [CVE-2025-62231](#)

### Fixes and Feature Changes in Yocto-5.0.15

- build-appliance-image: Update to scarthgap head revision
- classes/create-spdx-2.2: Define `SPDX_VERSION` to 2.2
- cml1.bbclass: use consistent make flags for menuconfig
- cross.bbclass: Propagate dependencies to outhash
- curl: Ensure 'CURL\_CA\_BUNDLE' from host env is indeed respected
- curl: Use host CA bundle by default for native(sdk) builds
- cve-check: extract extending [CVE\\_STATUS](#) to library function
- dev-manual/layers.rst: document "bitbake-layers show-machines"
- dev-manual/new-recipe.rst: replace 'bitbake -e' with 'bitbake-getvar'
- dev-manual/new-recipe.rst: typo, "whith" -> "which"
- dev-manual/new-recipe.rst: update "recipetool -h" output
- dev-manual/sbom.rst: reflect that create-spdx is enabled by default
- dev-manual: debugging: use bitbake-getvar in Viewing Variable Values section
- documentation: link to the Releases page on yoctoproject.org instead of wiki
- glslang: fix compiling with gcc15
- go: add sdk test
- go: extend runtime test
- go: remove duplicate arch map in sdk test
- goarch.bbclass: do not leak [TUNE\\_FEATURES](#) into crosssdk task signatures
- kernel-dev: add disable config example
- kernel-dev: common: migrate bitbake -e to bitbake-getvar
- kernel.bbclass: Add task to export kernel configuration to [SPDX](#)
- libssh2: fix regression in KEX method validation (GH-1553)



- libssh2: upgrade to 1.11.1
- migration-guides: add release notes for 4.0.31 and 5.0.13
- oe/sdk: fix empty SDK manifests
- oeqa/sdk/buildepox: skip test in eSDK
- oeqa/selftest: oe-selftest: Add *SPDX* tests for kernel config and *PACKAGECONFIG*
- oeqa: drop unnecessary dependency from go runtime tests
- oeqa: fix package detection in go sdk tests
- overview-manual: migrate to SVG + fix typo
- poky.conf: bump version for 5.0.15
- ref-manual: variables: migrate the *OVERRIDES* note to bitbake-getvar
- ruby: Upgrade to 3.3.10
- rust-target-config: fix nativesdk-libstd-rs build with baremetal
- scripts/install-buildtools: Update to 5.0.14
- spdx30: Provide software\_packageUrl field in *SPDX* 3.0 SBOM
- spdx30: fix cve status for patch files in VEX
- spdx30: provide all CVE\_STATUS, not only Patched status
- spdx30\_tasks: Add support for exporting *PACKAGECONFIG* to *SPDX*
- spdx: Revert "spdx: Update for bitbake changes"
- spdx: extend *CVE\_STATUS* variables
- testsdk: allow user to specify which tests to run
- vex.bbclass: add a new class
- vex: fix rootfs manifest
- xserver-xorg: remove redundant patch

### Known Issues in Yocto-5.0.15

- N/A

### Contributors to Yocto-5.0.15

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Aleksandar Nikolic
- Alexander Kanavin
- Benjamin Robin (Schneider Electric)
- Changqing Li

- Daniel Turull
- Deepak Rathore
- Deepesh Varatharajan
- Enrico Jörns
- Gyorgy Sarvari
- Hitendra Prajapati
- Hongxu Jia
- Hugo SIMELIERE
- Jiaying Song
- Kai Kang
- Kamel Bouhara (Schneider Electric)
- Lee Chee Yang
- Martin Jansa
- Mingli Yu
- Moritz Haase
- Osama Abdelkader
- Ovidiu Panait
- Peter Marko
- Praveen Kumar
- Quentin Schulz
- Robert P. J. Day
- Ross Burton
- Steve Sakoman
- Vijay Anusuri
- Walter Werner SCHNEIDER
- Yash Shinde
- Yogita Urade

## **Repositories / Downloads for Yocto-5.0.15**

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.15](#)

- Git Revision: [b0f5cc276639916df197435780b3e94accd4af41](#)
- Release Artefact: [yocto-docs-b0f5cc276639916df197435780b3e94accd4af41](#)
- sha: [28ebedfa6471e4ed7583aca0925cd31f4429af3d27ffc0a7e250f7b75404edd7](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.15/yocto-docs-b0f5cc276639916df197435780b3e94accd4af41.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.0.15/yocto-docs-b0f5cc276639916df197435780b3e94accd4af41.tar.bz2>

#### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.15](#)
- Git Revision: [72983ac391008ebceb45edc7a8f0f6d5f4fe715c](#)
- Release Artefact: [poky-72983ac391008ebceb45edc7a8f0f6d5f4fe715c](#)
- sha: [d5336d1ef1dd48b88cb92748c669360901004d458b7786ddc1918da12fef4edd](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.15/poky-72983ac391008ebceb45edc7a8f0f6d5f4fe715c.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.0.15/poky-72983ac391008ebceb45edc7a8f0f6d5f4fe715c.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.15](#)
- Git Revision: [6988157ad983978ffd6b12bcefedd4deaffdbbd1](#)
- Release Artefact: [oecore-6988157ad983978ffd6b12bcefedd4deaffdbbd1](#)
- sha: [98a691ce87f9aba57007e91b56bbe0af6d6c8f62aacb68820026478ff8e1f819](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.15/oecore-6988157ad983978ffd6b12bcefedd4deaffdbbd1.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.0.15/oecore-6988157ad983978ffd6b12bcefedd4deaffdbbd1.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>

- Branch: `scarthgap`
- Tag: `yocto-5.0.15`
- Git Revision: `9bb6e6e8b016a0c9dfe290369a6ed91ef4020535`
- Release Artefact: `meta-yocto-9bb6e6e8b016a0c9dfe290369a6ed91ef4020535`
- sha: `01778c43673ef11ec5d0fb76bd7c600031f5fc9bcfd9bfa586d5fb6b6babff95`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.15/meta-yocto-9bb6e6e8b016a0c9dfe290369a6ed91ef4020535.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.0.15/meta-yocto-9bb6e6e8b016a0c9dfe290369a6ed91ef4020535.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.15`
- Git Revision: `bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- Release Artefact: `meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- sha: `ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.15/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.0.15/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.8`
- Tag: `yocto-5.0.15`
- Git Revision: `8dcf084522b9c66a6639b5f117f554fde9b6b45a`
- Release Artefact: `bitbake-8dcf084522b9c66a6639b5f117f554fde9b6b45a`
- sha: `766eda21f2a914276d2723b1d8248be11507f954aef8fc5bb1767f3cb65688dd`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.15/bitbake-8dcf084522b9c66a6639b5f117f554fde9b6b45a.tar.bz2>

<https://mirrors.kernel.org/yocto/yocto/yocto-5.0.15/bitbake-8dcf084522b9c66a6639b5f117f554fde9b6b45a.tar.bz2>

### 17.7.18 Release notes for Yocto-5.0.16 (Scarthgap)

This release breaks support for Ubuntu 20.04 as a *compatible host*. The Ubuntu 20.04 Linux kernel headers are not recent enough to support the latest *pseudo* fixes.

Ubuntu 20.04 is End-of-Life since 31 May 2025. Impacted users are encouraged to upgrade to an actively supported host distribution. See *Requisiti di Sistema* for more information on compatible hosts.

Alternatively, a fix has been merged to scarthgap branch and can be applied on top of this release:

- <https://git.openembedded.org/openembedded-core/commit/?h=scarthgap&id=fe2666749094e896736ff24d6885419905488723>
- <https://git.yoctoproject.org/poky/commit/?h=scarthgap&id=65c3ebea05dde5cbc9d249e7949fabbc0047313e>

#### Security Fixes in Yocto-5.0.16

- curl: Fix CVE-2025-10148, CVE-2025-14017, CVE-2025-14524, CVE-2025-14819, CVE-2025-15079 and CVE-2025-15224
- dropbear: Fix CVE-2019-6111
- expat: Fix CVE-2026-24515 and CVE-2026-25210
- ffmpeg: Ignore CVE-2025-25469
- glib-2.0: Fix CVE-2025-13601, CVE-2025-14087, CVE-2025-14512 and CVE-2026-0988
- glibc: Fix CVE-2025-15281, CVE-2026-0861 and CVE-2026-0915
- inetutils: Fix CVE-2026-24061
- libarchive: Fix CVE-2025-60753 (follow-up fix)
- libpcap: Fix CVE-2025-11961 and CVE-2025-11964
- libpng: Fix CVE-2026-22695 and CVE-2026-22801
- libtasn1: Fix CVE-2025-13151
- libxml2: Fix CVE-2026-0989, CVE-2026-0990 and CVE-2026-0992
- python-urllib3: Fix for CVE-2026-21441
- python3: Fix CVE-2025-12084, CVE-2025-13836 and CVE-2025-13837
- qemu: Ignore CVE-2025-54566 and CVE-2025-54567
- util-linux: Fix CVE-2025-14104
- zlib: Ignore CVE-2026-22184

#### Fixes in Yocto-5.0.16

- bitbake: knotty: Make sure getTerminalColumns() returns two integers
- bitbake: knotty: fix TIOCGWINSZ call for Python 3.14 and later
- build-appliance-image: Update to scarthgap head revision
- contributor-guide/recipe-style-guide.rst: explain difference between layer and recipe license(s)

- contributor-guide/submit-changes.rst: remove mention of Upstream-Status
- cups: allow unknown directives in conf files
- dev-manual/packages.rst: fix example recipe version
- dev-manual/packages.rst: pr server: fix and explain why r0.X increments on *SRCREV* change
- dev-manual/packages.rst: rename r0.0 to r0 when *PR* server is not enabled
- dev-manual/temporary-source-code.rst: fix definition of *WORKDIR*
- docbook-xml-dtd4: fix the fetching failure
- docs: Add a new "Security" section
- docs: Makefile: fix rsvg-convert --format capitalization
- ffmpeg: upgrade to 6.1.4
- glibc: stable 2.39 branch updates
- improve\_kernel\_cve\_report: add script for postprocessing of kernel CVE data
- libtheora: set *CVE\_PRODUCT*
- lighttpd: Fix trailing slash on files in mod\_dirlisting
- meta/classes: fix missing vardeps for CVE status variables
- migration-guides: add release notes for 4.0.32, 5.0.14 and 5.0.15
- overview-manual/yp-intro.rst: change removed ECOSYSTEM to ABOUT
- overview-manual/yp-intro.rst: fix SDK type in bullet list
- overview-manual/yp-intro.rst: link to YP members and participants
- overview-manual: convert YP-flow-diagram.png to SVG
- pseudo: Add hard sstate dependencies for pseudo-native
- pseudo: Update to 1.9.3 release
- ref-manual/classes.rst: document the image-container class
- ref-manual/release-process.rst: add a "Development Cycle" section
- ref-manual/svg/releases.svg: mark styhead and walnascar EOL
- ref-manual/svg/releases.svg: mark whinlatter as current release
- ref-manual/variables.rst: document the *CCACHE\_TOP\_DIR* variable
- sdk-manual: appending-customizing: use none lexer for BitBake code blocks
- sdk-manual: appendix-obtain: fix default path for eSDK installer script
- sdk-manual: appendix-obtain: replace directory structure PNG with a parsed-literal block
- sdk-manual: appendix-obtain: replace eSDK directory structure PNG with a parsed-literal block
- sdk-manual: appendix-obtain: use parsed-literal block for naming convention of the installer scripts

- sdk-manual: delete sdk-title PNG
- sdk-manual: fix improper indent of general form of tarball installer scripts
- sdk-manual: fix incorrect highlight language for console code-blocks
- sdk-manual: fix incorrect highlight language for text code-blocks
- sdk-manual: replace sdk-environment PNG with SVG
- sdk-manual: using: fix SDK filename example
- sdk-manual: working-projects: properly highlight code code-blocks
- test-manual/ptest.rst: detail the exit code and output requirements
- zlib: Add *CVE\_PRODUCT* to exclude false positives
- zlib: cleanup obsolete CVE\_STATUS[CVE-2023-45853]

### Known Issues in Yocto-5.0.16

The poky *DISTRO\_VERSION* was incorrectly left at 5.0.15. This is a minor issue, if a workaround is needed please cherry-pick:

- poky                      commit                      <https://git.yoctoproject.org/poky/commit/?h=scarthgap&id=06210079b2e10d6d3fb943afe87864267e329821>
- meta-yocto              commit                      <https://git.yoctoproject.org/meta-yocto/commit/?h=scarthgap&id=03f93c769ec99e5086e492d8145eb308a718e8d3>

### Contributors to Yocto-5.0.16

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Amaury Couderc
- Ankur Tyagi
- Antonin Godard
- Benjamin Robin (Schneider Electric)
- Daniel Turull
- Enrico Scholz
- Fred Bacon
- Het Patel
- Hitendra Prajapati
- Hugo SIMELIERE
- Ken Kurematsu
- Khai Dang

- Lee Chee Yang
- Paul Barker
- Peter Marko
- Quentin Schulz
- Richard Purdie
- Robert Yang
- Vijay Anusuri
- Yoann Congal
- Zoltan Boszormenyi

## Repositories / Downloads for Yocto-5.0.16

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.16](#)
- Git Revision: [369f3307368eaea605983e80047377fd19ebd6bf](#)
- Release Artefact: [yocto-docs-369f3307368eaea605983e80047377fd19ebd6bf](#)
- sha: [e8ea8e2d5da2bfad868178d6fb37093c4f9ff06553f68970f0f730d6fb5cbd26](#)
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.16/yocto-docs-369f3307368eaea605983e80047377fd19ebd6bf.tar.bz2>
  - <https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.16/yocto-docs-369f3307368eaea605983e80047377fd19ebd6bf.tar.bz2>

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.16](#)
- Git Revision: [1d54d1c4736a114e1cecbe85a0306e3814d5ce70](#)
- Release Artefact: [poky-1d54d1c4736a114e1cecbe85a0306e3814d5ce70](#)
- sha: [efb75697fa7a8e35a3f46abcfa706400f56ae1d1b5e360b48d6ffa81f6a675e8](#)
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.16/poky-1d54d1c4736a114e1cecbe85a0306e3814d5ce70.tar.bz2>



<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.16/poky-1d54d1c4736a114e1cecbe85a0306e3814d5ce70.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.16`
- Git Revision: `a1f4ae4e569bc0e36c27c1e4651e502e54d63b28`
- Release Artefact: `oecore-a1f4ae4e569bc0e36c27c1e4651e502e54d63b28`
- sha: `10eefd2296206e5cbaf138de7dbd0dbe7bfc413618e924a123cd3f7f9a8418e0`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.16/oecore-a1f4ae4e569bc0e36c27c1e4651e502e54d63b28.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.16/oecore-a1f4ae4e569bc0e36c27c1e4651e502e54d63b28.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `scarthgap`
- Tag: `yocto-5.0.16`
- Git Revision: `9bb6e6e8b016a0c9dfe290369a6ed91ef4020535`
- Release Artefact: `meta-yocto-9bb6e6e8b016a0c9dfe290369a6ed91ef4020535`
- sha: `d9cfd2192d12ebc55553bc421f3ab00d1f49c5f5c4c70e48923da695d19e8e2a`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.16/meta-yocto-9bb6e6e8b016a0c9dfe290369a6ed91ef4020535.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.16/meta-yocto-9bb6e6e8b016a0c9dfe290369a6ed91ef4020535.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.16`
- Git Revision: `bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- Release Artefact: `meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- sha: `ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.16/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.16/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0.16
- Git Revision: 10118785e4a670bce4980e1044c0888a8b6e84af
- Release Artefact: bitbake-10118785e4a670bce4980e1044c0888a8b6e84af
- sha: 601a16210d7dc9b7a7306240d3e7013b3f950db8953fdd972151d715e050cc39
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.16/bitbake-10118785e4a670bce4980e1044c0888a8b6e84af.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.16/bitbake-10118785e4a670bce4980e1044c0888a8b6e84af.tar.bz2>

### 17.7.19 Release notes for Yocto-5.0.17 (Scarthgap)

Openssl 3.2 has reached EOL. Some projects would like to use LTS version due to criticality and exposure of this component, so upgrade to 3.5 branch.

#### Security Fixes in Yocto-5.0.17

- alsa-lib: Fix CVE-2026-25068
- avahi: Fix CVE-2025-68276, CVE-2025-68468, CVE-2025-68471 and CVE-2026-24401
- bind: Fix CVE-2025-13878
- busybox: Fix CVE-2025-60876
- ffmpeg: ignore CVE-2025-1594, CVE-2025-10256, CVE-2025-12343 and CVE-2025-25468
- freetype: Fix CVE-2026-23865
- gdk-pixbuf: Fix CVE-2025-6199
- glib-2.0: Fix CVE-2026-1484, CVE-2026-1485 and CVE-2026-1489
- gnupg: Fix CVE-2025-68973
- gnutls: Fix CVE-2025-14831
- go 1.22.12: Fix CVE-2025-61726, CVE-2025-61728, CVE-2025-61730, CVE-2025-61731, CVE-2025-61732, CVE-2025-68119 and CVE-2025-68121

- harfbuzz: Fix CVE-2026-22693
- inetutils: Fix CVE-2026-28372 and CVE-2026-32746
- libpng: Fix CVE-2026-25646
- libsndfile1: Fix CVE-2025-56226
- libtheora: Ignore CVE-2024-56431
- linux-yocto/6.6: Fix CVE-2025-38593, CVE-2025-38643, CVE-2025-38678, CVE-2025-40039, CVE-2025-40040, CVE-2025-40149, CVE-2025-40164, CVE-2025-40251, CVE-2025-68211, CVE-2025-68214, CVE-2025-68223, CVE-2025-68340, CVE-2025-68365, CVE-2025-68725, CVE-2025-68817, CVE-2025-71068, CVE-2025-71071, CVE-2025-71075, CVE-2025-71077, CVE-2025-71078, CVE-2025-71079, CVE-2025-71081, CVE-2025-71082, CVE-2025-71083, CVE-2025-71084, CVE-2025-71085, CVE-2025-71086, CVE-2025-71087, CVE-2025-71088, CVE-2025-71089, CVE-2025-71091, CVE-2025-71093, CVE-2025-71094, CVE-2025-71095, CVE-2025-71096, CVE-2025-71097, CVE-2025-71098, CVE-2025-71101, CVE-2025-71102, CVE-2025-71104, CVE-2025-71105, CVE-2025-71107, CVE-2025-71108, CVE-2025-71111, CVE-2025-71112, CVE-2025-71113, CVE-2025-71114, CVE-2025-71116, CVE-2025-71118, CVE-2025-71119, CVE-2025-71120, CVE-2025-71121, CVE-2025-71122, CVE-2025-71125, CVE-2025-71126, CVE-2025-71127, CVE-2025-71129, CVE-2025-71130, CVE-2025-71131, CVE-2025-71132, CVE-2025-71133, CVE-2025-71136, CVE-2025-71137, CVE-2025-71138, CVE-2025-71141, CVE-2025-71143, CVE-2025-71147, CVE-2025-71148, CVE-2025-71149, CVE-2025-71150, CVE-2025-71151, CVE-2025-71153, CVE-2025-71154, CVE-2025-71160, CVE-2025-71162, CVE-2025-71163, CVE-2025-71180, CVE-2025-71182, CVE-2025-71183, CVE-2025-71185, CVE-2025-71186, CVE-2025-71188, CVE-2025-71189, CVE-2025-71190, CVE-2025-71191, CVE-2025-71200, CVE-2026-22976, CVE-2026-22977, CVE-2026-22978, CVE-2026-22979, CVE-2026-22980, CVE-2026-22982, CVE-2026-22984, CVE-2026-22990, CVE-2026-22991, CVE-2026-22992, CVE-2026-22994, CVE-2026-22997, CVE-2026-22998, CVE-2026-22999, CVE-2026-23001, CVE-2026-23003, CVE-2026-23005, CVE-2026-23006, CVE-2026-23010, CVE-2026-23011, CVE-2026-23019, CVE-2026-23020, CVE-2026-23021, CVE-2026-23025, CVE-2026-23026, CVE-2026-23060, CVE-2026-23061, CVE-2026-23062, CVE-2026-23063, CVE-2026-23064, CVE-2026-23068, CVE-2026-23069, CVE-2026-23071, CVE-2026-23073, CVE-2026-23074, CVE-2026-23075, CVE-2026-23076, CVE-2026-23078, CVE-2026-23080, CVE-2026-23083, CVE-2026-23084, CVE-2026-23085, CVE-2026-23086, CVE-2026-23087, CVE-2026-23088, CVE-2026-23089, CVE-2026-23090, CVE-2026-23091, CVE-2026-23093, CVE-2026-23094, CVE-2026-23095, CVE-2026-23096, CVE-2026-23097, CVE-2026-23098, CVE-2026-23099, CVE-2026-23101, CVE-2026-23102, CVE-2026-23103, CVE-2026-23105, CVE-2026-23107, CVE-2026-23108, CVE-2026-23110, CVE-2026-23113, CVE-2026-23116, CVE-2026-23119, CVE-2026-23120, CVE-2026-23121, CVE-2026-23123, CVE-2026-23124, CVE-2026-23125, CVE-2026-23126, CVE-2026-23128, CVE-2026-23131, CVE-2026-23133, CVE-2026-23135, CVE-2026-23136, CVE-2026-23139, CVE-2026-23140, CVE-2026-23141, CVE-2026-23142, CVE-2026-23144, CVE-2026-23146, CVE-2026-23150, CVE-2026-23156, CVE-2026-23160, CVE-2026-23163, CVE-2026-23164, CVE-2026-23167, CVE-2026-23168, CVE-2026-23170, CVE-2026-23172, CVE-2026-23173 and CVE-2026-23212
- openssl: fix CVE-2025-15468 and CVE-2025-69419
- python3-cryptography: Fix CVE-2026-26007
- python3-pip: Fix CVE-2026-1703

- python3-pyopenssl: Fix [CVE-2026-27448](#) and [CVE-2026-27459](#)
- tiff: ignore [CVE-2025-61144](#) and [CVE-2025-61145](#)
- vim: ignore [CVE-2025-66476](#)
- zlib: Fix [CVE-2026-27171](#)

### Fixes in Yocto-5.0.17

- README: Add scarthgap subject-prefix to git-send-email suggestion
- bind: upgrade to 9.18.44
- bitbake: COW: Fix hardcoded magic numbers and work with python 3.13
- bitbake: fetch2: Fix LFS object checkout in submodules
- bitbake: fetch2: Fix incorrect lfs parametrization for submodules
- bitbake: fetch2: don't try to preserve all attributes when unpacking files
- bitbake: git-sm: Add clean function
- build-appliance-image: Update to scarthgap head revision
- classes/buildhistory: Do not sign buildhistory commits
- create-pull-request: Keep commit hash to be pulled in cover email
- dev-manual: delete references to "tar" package format
- docs: Makefile: pass -silent to latexmk
- go-vendor: Fix absolute paths issue
- improve\_kernel\_cve\_report: add option to read debugsources.zstd
- improve\_kernel\_cve\_report: do not override backported-patch
- improve\_kernel\_cve\_report: do not use custom version
- linux-yocto/6.6: upgrade to v6.6.123
- lsb.py: strip ' from os-release file
- migration-guides: add release notes for 5.0.16
- mobile-broadband-provider-info: upgrade to 20251101
- oe-setup-build: Fix typo
- oeqa/selftest/wic: test recursive dir copy on ext partitions
- openssl: upgrade to 3.5.5
- overview-manual/concepts: list other possible class directories
- overview-manual: escape wildcard in inline markup
- poky.conf: Bump version for 5.0.17 release
- poky.conf: add Centos Stream 9, fedora-41, rocky-8 to *SANITY\_TESTED\_DISTROS*

- pseudo: Update to include a fix for systems with kernel <5.6
- python3-pip: drop unused Windows distlib launcher templates
- python3-setuptools: drop Windows launcher executables on non-mingw builds
- ref-manual/classes.rst: fix broken links to U-Boot documentation
- ref-manual/system-requirements.rst: update supported, end-of-life and untested distros
- scripts/install-buildtools: Update to 5.0.15
- spdx30\_tasks: Exclude 'doc' when exporting *PACKAGECONFIG* to *SPDX*
- spdx: add option to include only compiled sources
- systemd-systemctl: Fix instance name parsing with escapes or periods
- tzdata,tzcode-native: upgrade to 2025c
- u-boot: move CVE Fixes out of the common .inc file
- uboot-config: Fix devtool modify
- weston: fix a touch-calibrator issue
- what-i-wish-id-known.rst: replace figure by the new SVG
- wic/engine: error on old host debugfs for standalone directory copy
- wic/engine: fix copying directories into wic image with ext\* partition
- wireless-regdb: upgrade to 2026.02.04

#### Known Issues in Yocto-5.0.17

- N/A

#### Contributors to Yocto-5.0.17

- Aleksandar Nikolic
- Amaury Couderc
- Ankur Tyagi
- Antonin Godard
- Benjamin Robin (Schneider Electric)
- Bruce Ashfield
- Daniel Dragomir
- Daniel Turull
- Deepak Rathore
- Dragomir, Daniel
- Eduardo Ferreira
- Fabio Berton

- Hitendra Prajapati
- Hugo SIMELIERE
- João Marcos Costa (Schneider Electric)
- Kristiyan Chakarov
- Krupal Ka Patel
- Lee Chee Yang
- Livin Sunny
- Martin Jansa
- Michael Opdenacker
- Ming Liu
- Nguyen Dat Tho
- Paul Barker
- Peter Marko
- Philip Lorenz
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Robert Yang
- Ross Burton
- Ryan Eatmon
- Shaik Moin
- Tom Hochstein
- Trent Piepho
- Vijay Anusuri
- Yoann Congal

## **Repositories / Downloads for Yocto-5.0.17**

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.17](#)
- Git Revision: [aa7226705451e6c1ef964d49963bbed29b267c27](#)
- Release Artefact: [yocto-docs-aa7226705451e6c1ef964d49963bbed29b267c27](#)

- sha: d429833609637657f213611317dfadbd70293fff2f9e22753d1f71ef8515a6c0

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.17/yocto-docs-aa7226705451e6c1ef964d49963bbed29b267c27.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.17/yocto-docs-aa7226705451e6c1ef964d49963bbed29b267c27.tar.bz2>

#### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: scarthgap
- Tag: yocto-5.0.17
- Git Revision: 1e8099846661571ede077f533eb1b6c86818ddce
- Release Artefact: poky-1e8099846661571ede077f533eb1b6c86818ddce
- sha: b56890576f593cc881ea8e467562d842cfca248099ce653d28ca14d250f6219e
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.17/poky-1e8099846661571ede077f533eb1b6c86818ddce.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.17/poky-1e8099846661571ede077f533eb1b6c86818ddce.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: scarthgap
- Tag: yocto-5.0.17
- Git Revision: 52380df998b3a8fe6a091f8547434a3231320a8e
- Release Artefact: oecore-52380df998b3a8fe6a091f8547434a3231320a8e
- sha: a948d75acf76a392d170129ce6eb6f5fe45082d95b4fd28045aac58b8373cb26
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.17/oecore-52380df998b3a8fe6a091f8547434a3231320a8e.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.17/oecore-52380df998b3a8fe6a091f8547434a3231320a8e.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: scarthgap
- Tag: yocto-5.0.17

- Git Revision: [c7c38663a1cafb1fa8593c0b246811e51d3bbe20](#)
- Release Artefact: [meta-yocto-c7c38663a1cafb1fa8593c0b246811e51d3bbe20](#)
- sha: [5a2a9360249e639694cc2a75985e3907085512b3eb236e8491cb07f1e0cb0f19](#)
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.17/meta-yocto-c7c38663a1cafb1fa8593c0b246811e51d3bbe20.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.17/meta-yocto-c7c38663a1cafb1fa8593c0b246811e51d3bbe20.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.17](#)
- Git Revision: [bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f](#)
- Release Artefact: [meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f](#)
- sha: [ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65](#)
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.17/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.17/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.8](#)
- Tag: [yocto-5.0.17](#)
- Git Revision: [d3b4c352dd33fca90cd31649eda054b884478739](#)
- Release Artefact: [bitbake-d3b4c352dd33fca90cd31649eda054b884478739](#)
- sha: [1021fc412780e21b25ccb045b66368ebe3fc4e785a65066ac0cafb9bdd5492fa](#)
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.17/bitbake-d3b4c352dd33fca90cd31649eda054b884478739.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.17/bitbake-d3b4c352dd33fca90cd31649eda054b884478739.tar.bz2>



## 17.7.20 Release notes for Yocto-5.0.18 (Scarthgap)

### Security Fixes in Yocto-5.0.18

The large number of CVE updates for the `linux-yocto` recipe is linked to two backport commits on *OpenEmbedded-Core (OE-Core)*. See [66a13f9](#) and [4bdf534](#) for more details on these changes.

- avahi: Fix CVE-2026-34933
- binutils: Fix CVE-2025-69647 and CVE-2025-69648
- binutils: Ignore CVE-2025-69650 and CVE-2025-69651
- busybox: Fix CVE-2026-26157 and CVE-2026-26158
- coreutils: set *CVE\_PRODUCT*
- curl: Fix CVE-2026-1965, CVE-2026-3783 and CVE-2026-3784
- expat: Fix CVE-2026-32776, CVE-2026-32777 and CVE-2026-32778
- gdk-pixbuf: Fix CVE-2026-5201
- gi-docgen: Fix CVE-2025-11687
- gnupg: Fix CVE-2026-24882
- inetutils: Fix CVE-2026-32772
- libarchive: Fix CVE-2026-4111 and CVE-2026-4426
- libpng: Fix CVE-2026-33636
- libsoup: Fix CVE-2025-14523 and CVE-2025-32049
- libxml2: Fix CVE-2026-1757
- linux-yocto/6.6: Fix CVE-2025-40005, CVE-2025-40082, CVE-2025-68358, CVE-2025-68823, CVE-2025-71204, CVE-2025-71220, CVE-2025-71222, CVE-2025-71223, CVE-2025-71229, CVE-2025-71232, CVE-2025-71233, CVE-2025-71235, CVE-2025-71236, CVE-2025-71237, CVE-2025-71238, CVE-2025-71268, CVE-2025-71270, CVE-2026-23100, CVE-2026-23111, CVE-2026-23112, CVE-2026-23169, CVE-2026-23187, CVE-2026-23190, CVE-2026-23193, CVE-2026-23198, CVE-2026-23200, CVE-2026-23202, CVE-2026-23204, CVE-2026-23205, CVE-2026-23206, CVE-2026-23209, CVE-2026-23216, CVE-2026-23220, CVE-2026-23221, CVE-2026-23222, CVE-2026-23228, CVE-2026-23229, CVE-2026-23230, CVE-2026-23233, CVE-2026-23234, CVE-2026-23235, CVE-2026-23236, CVE-2026-23237, CVE-2026-23238, CVE-2026-23256, CVE-2026-23257, CVE-2026-23261, CVE-2026-23262 and CVE-2026-31687
- linux-yocto/6.6: Ignore CVE-2020-36788, CVE-2020-36789, CVE-2020-36790, CVE-2020-36791, CVE-2021-4439, CVE-2021-4440, CVE-2021-4441, CVE-2021-4442, CVE-2021-4453, CVE-2021-4454, CVE-2021-4460, CVE-2021-47181, CVE-2021-47182, CVE-2021-47183, CVE-2021-47184, CVE-2021-47185, CVE-2021-47186, CVE-2021-47187, CVE-2021-47188, CVE-2021-47189, CVE-2021-47190, CVE-2021-47191, CVE-2021-47192, CVE-2021-47193, CVE-2021-47194, CVE-2021-47195, CVE-2021-47196, CVE-2021-47197, CVE-2021-47198, CVE-2021-47199, CVE-2021-47200, CVE-2021-47201, CVE-2021-47202, CVE-2021-47203, CVE-2021-47204, CVE-2021-47205, CVE-2021-47206, CVE-2021-47207,



17.7. Release 5.0 (scarthgap) 1419

- [illegible]

17.7. Release 5.0 (scarthgap) 1421

49218, CVE-2022-49219, CVE-2022-49220, CVE-2022-49221, CVE-2022-49222, CVE-2022-49223, CVE-2022-49224, CVE-2022-49225, CVE-2022-49226, CVE-2022-49227, CVE-2022-49228, CVE-2022-49229, CVE-2022-49230, CVE-2022-49231, CVE-2022-49232, CVE-2022-49233, CVE-2022-49234, CVE-2022-49235, CVE-2022-49236, CVE-2022-49237, CVE-2022-49238, CVE-2022-49239, CVE-2022-49240, CVE-2022-49241, CVE-2022-49242, CVE-2022-49243, CVE-2022-49244, CVE-2022-49245, CVE-2022-49246, CVE-2022-49247, CVE-2022-49248, CVE-2022-49249, CVE-2022-49250, CVE-2022-49251, CVE-2022-49252, CVE-2022-49253, CVE-2022-49254, CVE-2022-49255, CVE-2022-49256 and CVE-2022-49257

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2022-49258, CVE-2022-49259, CVE-2022-49260, CVE-2022-49261, CVE-2022-49262, CVE-2022-49263, CVE-2022-49264, CVE-2022-49265, CVE-2022-49266, CVE-2022-49268, CVE-2022-49269, CVE-2022-49270, CVE-2022-49271, CVE-2022-49272, CVE-2022-49273, CVE-2022-49274, CVE-2022-49275, CVE-2022-49276, CVE-2022-49277, CVE-2022-49278, CVE-2022-49279, CVE-2022-49280, CVE-2022-49281, CVE-2022-49282, CVE-2022-49283, CVE-2022-49284, CVE-2022-49285, CVE-2022-49286, CVE-2022-49287, CVE-2022-49288, CVE-2022-49289, CVE-2022-49290, CVE-2022-49291, CVE-2022-49292, CVE-2022-49293, CVE-2022-49294, CVE-2022-49295, CVE-2022-49296, CVE-2022-49297, CVE-2022-49298, CVE-2022-49300, CVE-2022-49301, CVE-2022-49302, CVE-2022-49303, CVE-2022-49304, CVE-2022-49305, CVE-2022-49306, CVE-2022-49307, CVE-2022-49308, CVE-2022-49309, CVE-2022-49310, CVE-2022-49311, CVE-2022-49312, CVE-2022-49313, CVE-2022-49314, CVE-2022-49315, CVE-2022-49316, CVE-2022-49317, CVE-2022-49318, CVE-2022-49319, CVE-2022-49320, CVE-2022-49321, CVE-2022-49322, CVE-2022-49323, CVE-2022-49324, CVE-2022-49325, CVE-2022-49326, CVE-2022-49327, CVE-2022-49328, CVE-2022-49329, CVE-2022-49330, CVE-2022-49331, CVE-2022-49332, CVE-2022-49333, CVE-2022-49334, CVE-2022-49335, CVE-2022-49336, CVE-2022-49337, CVE-2022-49338, CVE-2022-49339, CVE-2022-49340, CVE-2022-49341, CVE-2022-49342, CVE-2022-49343, CVE-2022-49344, CVE-2022-49345, CVE-2022-49346, CVE-2022-49347, CVE-2022-49348, CVE-2022-49349, CVE-2022-49350, CVE-2022-49351, CVE-2022-49352, CVE-2022-49353, CVE-2022-49354, CVE-2022-49356, CVE-2022-49357, CVE-2022-49358, CVE-2022-49359, CVE-2022-49360, CVE-2022-49361, CVE-2022-49362, CVE-2022-49363, CVE-2022-49364, CVE-2022-49365, CVE-2022-49366, CVE-2022-49367, CVE-2022-49368, CVE-2022-49369, CVE-2022-49370, CVE-2022-49371, CVE-2022-49372, CVE-2022-49373, CVE-2022-49374, CVE-2022-49375, CVE-2022-49376, CVE-2022-49377, CVE-2022-49378, CVE-2022-49379, CVE-2022-49380, CVE-2022-49381, CVE-2022-49382, CVE-2022-49383, CVE-2022-49384, CVE-2022-49385, CVE-2022-49386, CVE-2022-49387, CVE-2022-49388, CVE-2022-49389, CVE-2022-49390, CVE-2022-49391, CVE-2022-49392, CVE-2022-49393, CVE-2022-49394, CVE-2022-49395, CVE-2022-49396, CVE-2022-49397, CVE-2022-49398, CVE-2022-49399, CVE-2022-49400, CVE-2022-49401, CVE-2022-49402, CVE-2022-49403, CVE-2022-49404, CVE-2022-49405, CVE-2022-49406, CVE-2022-49407, CVE-2022-49408, CVE-2022-49409, CVE-2022-49410, CVE-2022-49411, CVE-2022-49412, CVE-2022-49413, CVE-2022-49414, CVE-2022-49415, CVE-2022-49416, CVE-2022-49417, CVE-2022-49418, CVE-2022-49419, CVE-2022-49420, CVE-2022-49421, CVE-2022-49422, CVE-2022-49423, CVE-2022-49424, CVE-2022-49425, CVE-2022-49426, CVE-2022-49427, CVE-2022-49428, CVE-2022-49429, CVE-2022-49430, CVE-2022-49431, CVE-2022-49432, CVE-2022-49433, CVE-2022-49434, CVE-2022-49435, CVE-2022-49436, CVE-2022-49437, CVE-2022-49438, CVE-2022-49439, CVE-2022-49440, CVE-2022-49441, CVE-2022-49442, CVE-2022-49443, CVE-2022-49444, CVE-2022-49445, CVE-2022-49446, CVE-2022-49447, CVE-2022-49448, CVE-2022-49449, CVE-2022-49450, CVE-2022-49451, CVE-2022-49452, CVE-2022-49453, CVE-2022-49454, CVE-2022-49455, CVE-2022-49456, CVE-2022-



17.7. Release 5.0 (scarthgap) 1423

CVE-2022-49709, CVE-2022-49710, CVE-2022-49711, CVE-2022-49712, CVE-2022-49713, CVE-2022-49714, CVE-2022-49715, CVE-2022-49716, CVE-2022-49717, CVE-2022-49718, CVE-2022-49719, CVE-2022-49720, CVE-2022-49721, CVE-2022-49722, CVE-2022-49723, CVE-2022-49724, CVE-2022-49725, CVE-2022-49726, CVE-2022-49727, CVE-2022-49728, CVE-2022-49729, CVE-2022-49731, CVE-2022-49732, CVE-2022-49733, CVE-2022-49738, CVE-2022-49739, CVE-2022-49740, CVE-2022-49741, CVE-2022-49742, CVE-2022-49743, CVE-2022-49744, CVE-2022-49745, CVE-2022-49746, CVE-2022-49747, CVE-2022-49748, CVE-2022-49749, CVE-2022-49750, CVE-2022-49751, CVE-2022-49752, CVE-2022-49753, CVE-2022-49754, CVE-2022-49755, CVE-2022-49756, CVE-2022-49757, CVE-2022-49758, CVE-2022-49759, CVE-2022-49760, CVE-2022-49761, CVE-2022-49762, CVE-2022-49763, CVE-2022-49764, CVE-2022-49765, CVE-2022-49766, CVE-2022-49767, CVE-2022-49768, CVE-2022-49769, CVE-2022-49770, CVE-2022-49771, CVE-2022-49772, CVE-2022-49773, CVE-2022-49774, CVE-2022-49775, CVE-2022-49776, CVE-2022-49777, CVE-2022-49778, CVE-2022-49779, CVE-2022-49780, CVE-2022-49781, CVE-2022-49782, CVE-2022-49783, CVE-2022-49784, CVE-2022-49785, CVE-2022-49786, CVE-2022-49787, CVE-2022-49788, CVE-2022-49789, CVE-2022-49790, CVE-2022-49791, CVE-2022-49792, CVE-2022-49793, CVE-2022-49794, CVE-2022-49795, CVE-2022-49796, CVE-2022-49797, CVE-2022-49798, CVE-2022-49799, CVE-2022-49800, CVE-2022-49801 and CVE-2022-49802

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2022-49803, CVE-2022-49804, CVE-2022-49805, CVE-2022-49806, CVE-2022-49807, CVE-2022-49808, CVE-2022-49809, CVE-2022-49810, CVE-2022-49811, CVE-2022-49812, CVE-2022-49813, CVE-2022-49814, CVE-2022-49815, CVE-2022-49817, CVE-2022-49818, CVE-2022-49819, CVE-2022-49820, CVE-2022-49821, CVE-2022-49822, CVE-2022-49823, CVE-2022-49824, CVE-2022-49825, CVE-2022-49826, CVE-2022-49827, CVE-2022-49828, CVE-2022-49829, CVE-2022-49830, CVE-2022-49831, CVE-2022-49832, CVE-2022-49833, CVE-2022-49834, CVE-2022-49835, CVE-2022-49836, CVE-2022-49837, CVE-2022-49838, CVE-2022-49839, CVE-2022-49840, CVE-2022-49841, CVE-2022-49842, CVE-2022-49844, CVE-2022-49845, CVE-2022-49846, CVE-2022-49847, CVE-2022-49848, CVE-2022-49849, CVE-2022-49850, CVE-2022-49851, CVE-2022-49852, CVE-2022-49853, CVE-2022-49854, CVE-2022-49855, CVE-2022-49857, CVE-2022-49858, CVE-2022-49859, CVE-2022-49860, CVE-2022-49861, CVE-2022-49862, CVE-2022-49863, CVE-2022-49864, CVE-2022-49865, CVE-2022-49866, CVE-2022-49867, CVE-2022-49868, CVE-2022-49869, CVE-2022-49870, CVE-2022-49871, CVE-2022-49872, CVE-2022-49873, CVE-2022-49874, CVE-2022-49875, CVE-2022-49876, CVE-2022-49877, CVE-2022-49878, CVE-2022-49879, CVE-2022-49880, CVE-2022-49881, CVE-2022-49882, CVE-2022-49883, CVE-2022-49884, CVE-2022-49885, CVE-2022-49886, CVE-2022-49887, CVE-2022-49888, CVE-2022-49889, CVE-2022-49890, CVE-2022-49891, CVE-2022-49892, CVE-2022-49893, CVE-2022-49894, CVE-2022-49895, CVE-2022-49896, CVE-2022-49898, CVE-2022-49899, CVE-2022-49900, CVE-2022-49901, CVE-2022-49902, CVE-2022-49903, CVE-2022-49904, CVE-2022-49905, CVE-2022-49906, CVE-2022-49907, CVE-2022-49908, CVE-2022-49910, CVE-2022-49911, CVE-2022-49912, CVE-2022-49913, CVE-2022-49914, CVE-2022-49915, CVE-2022-49916, CVE-2022-49917, CVE-2022-49918, CVE-2022-49919, CVE-2022-49920, CVE-2022-49921, CVE-2022-49922, CVE-2022-49923, CVE-2022-49924, CVE-2022-49925, CVE-2022-49926, CVE-2022-49927, CVE-2022-49928, CVE-2022-49929, CVE-2022-49930, CVE-2022-49931, CVE-2022-49932, CVE-2022-49934, CVE-2022-49935, CVE-2022-49936, CVE-2022-49937, CVE-2022-49938, CVE-2022-49939, CVE-2022-49940, CVE-2022-49942, CVE-2022-49943, CVE-2022-49944, CVE-2022-49945, CVE-2022-49946, CVE-2022-49947, CVE-2022-49948, CVE-2022-49949, CVE-2022-49950, CVE-2022-49951, CVE-2022-49952, CVE-2022-49953, CVE-2022-49954, CVE-2022-49955, CVE-2022-49956,



## 17.7. Release 5.0 (scarthgap) 1425



17.7. Release 5.0 (scarthgap) 1427

CVE-2022-50757, CVE-2022-50758, CVE-2022-50759, CVE-2022-50760, CVE-2022-50761, CVE-2022-50762, CVE-2022-50763, CVE-2022-50764, CVE-2022-50765, CVE-2022-50766, CVE-2022-50767, CVE-2022-50768, CVE-2022-50769, CVE-2022-50770, CVE-2022-50771, CVE-2022-50772, CVE-2022-50773, CVE-2022-50774, CVE-2022-50775, CVE-2022-50776, CVE-2022-50777, CVE-2022-50778, CVE-2022-50779, CVE-2022-50780, CVE-2022-50781, CVE-2022-50782, CVE-2022-50783, CVE-2022-50784, CVE-2022-50785, CVE-2022-50786, CVE-2022-50809, CVE-2022-50810, CVE-2022-50811, CVE-2022-50812, CVE-2022-50813, CVE-2022-50814, CVE-2022-50815, CVE-2022-50816, CVE-2022-50817, CVE-2022-50818, CVE-2022-50819, CVE-2022-50820, CVE-2022-50821, CVE-2022-50822, CVE-2022-50823, CVE-2022-50824, CVE-2022-50825, CVE-2022-50826, CVE-2022-50827, CVE-2022-50828, CVE-2022-50829, CVE-2022-50830, CVE-2022-50832, CVE-2022-50833, CVE-2022-50834, CVE-2022-50835, CVE-2022-50836, CVE-2022-50837, CVE-2022-50838, CVE-2022-50839, CVE-2022-50840, CVE-2022-50841, CVE-2022-50842, CVE-2022-50843, CVE-2022-50844, CVE-2022-50845, CVE-2022-50846, CVE-2022-50847, CVE-2022-50848, CVE-2022-50849, CVE-2022-50850, CVE-2022-50851, CVE-2022-50852, CVE-2022-50853, CVE-2022-50854, CVE-2022-50855, CVE-2022-50856, CVE-2022-50857, CVE-2022-50858, CVE-2022-50859, CVE-2022-50860, CVE-2022-50861, CVE-2022-50862, CVE-2022-50863, CVE-2022-50864, CVE-2022-50865, CVE-2022-50866, CVE-2022-50867, CVE-2022-50868, CVE-2022-50869, CVE-2022-50870, CVE-2022-50871, CVE-2022-50872, CVE-2022-50873, CVE-2022-50874, CVE-2022-50875, CVE-2022-50876, CVE-2022-50877, CVE-2022-50878, CVE-2022-50879, CVE-2022-50880, CVE-2022-50881, CVE-2022-50882, CVE-2022-50883, CVE-2022-50884, CVE-2022-50885, CVE-2022-50886, CVE-2022-50887, CVE-2022-50888, CVE-2022-50889, CVE-2023-4130, CVE-2023-4515, CVE-2023-7324, CVE-2023-32246, CVE-2023-32249, CVE-2023-52585, CVE-2023-52634, CVE-2023-52642, CVE-2023-52643, CVE-2023-52644, CVE-2023-52645, CVE-2023-52646, CVE-2023-52647, CVE-2023-52648, CVE-2023-52649, CVE-2023-52650, CVE-2023-52652, CVE-2023-52653, CVE-2023-52654, CVE-2023-52655, CVE-2023-52656, CVE-2023-52657, CVE-2023-52658, CVE-2023-52659, CVE-2023-52660, CVE-2023-52661, CVE-2023-52662, CVE-2023-52663, CVE-2023-52664, CVE-2023-52667, CVE-2023-52668, CVE-2023-52669, CVE-2023-52670, CVE-2023-52671, CVE-2023-52672, CVE-2023-52673, CVE-2023-52674, CVE-2023-52675, CVE-2023-52676, CVE-2023-52677, CVE-2023-52678, CVE-2023-52679, CVE-2023-52680, CVE-2023-52681, CVE-2023-52682, CVE-2023-52683, CVE-2023-52684, CVE-2023-52686, CVE-2023-52687, CVE-2023-52688, CVE-2023-52689, CVE-2023-52690, CVE-2023-52691, CVE-2023-52692, CVE-2023-52693, CVE-2023-52694, CVE-2023-52695, CVE-2023-52696, CVE-2023-52697, CVE-2023-52698, CVE-2023-52699, CVE-2023-52700, CVE-2023-52701, CVE-2023-52702, CVE-2023-52703, CVE-2023-52704, CVE-2023-52705, CVE-2023-52706, CVE-2023-52707, CVE-2023-52708, CVE-2023-52730, CVE-2023-52731, CVE-2023-52732, CVE-2023-52735, CVE-2023-52736, CVE-2023-52737, CVE-2023-52738 and CVE-2023-52739

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2023-52740, CVE-2023-52741, CVE-2023-52742, CVE-2023-52743, CVE-2023-52744, CVE-2023-52745, CVE-2023-52746, CVE-2023-52747, CVE-2023-52748, CVE-2023-52749, CVE-2023-52750, CVE-2023-52751, CVE-2023-52752, CVE-2023-52753, CVE-2023-52754, CVE-2023-52755, CVE-2023-52757, CVE-2023-52760, CVE-2023-52761, CVE-2023-52762, CVE-2023-52763, CVE-2023-52764, CVE-2023-52765, CVE-2023-52766, CVE-2023-52767, CVE-2023-52768, CVE-2023-52769, CVE-2023-52770, CVE-2023-52771, CVE-2023-52772, CVE-2023-52773, CVE-2023-52774, CVE-2023-52775, CVE-2023-52776, CVE-2023-52777, CVE-2023-52778, CVE-2023-52779, CVE-2023-52780, CVE-2023-52781, CVE-2023-52782, CVE-2023-52783, CVE-2023-52784, CVE-2023-52785, CVE-2023-52786, CVE-2023-52787, CVE-2023-52788, CVE-2023-52789, CVE-2023-52790,

## 17.7. Release 5.0 (scarthgap) 1429





- 17.7. Release 5.0 (scarthgap) 1431





53864, CVE-2023-53865, CVE-2023-53866, CVE-2023-53867, CVE-2023-53986, CVE-2023-53987, CVE-2023-53988, CVE-2023-53989, CVE-2023-53990, CVE-2023-53991, CVE-2023-53992, CVE-2023-53993, CVE-2023-53994, CVE-2023-53995, CVE-2023-53996, CVE-2023-53997, CVE-2023-53998, CVE-2023-53999, CVE-2023-54000, CVE-2023-54001, CVE-2023-54002, CVE-2023-54003, CVE-2023-54004, CVE-2023-54005, CVE-2023-54006, CVE-2023-54007, CVE-2023-54008, CVE-2023-54009, CVE-2023-54010, CVE-2023-54011, CVE-2023-54012, CVE-2023-54013, CVE-2023-54014, CVE-2023-54015, CVE-2023-54016, CVE-2023-54017, CVE-2023-54018, CVE-2023-54019, CVE-2023-54020 and CVE-2023-54021

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2023-54022, CVE-2023-54023, CVE-2023-54024, CVE-2023-54025, CVE-2023-54026, CVE-2023-54027, CVE-2023-54028, CVE-2023-54030, CVE-2023-54031, CVE-2023-54032, CVE-2023-54033, CVE-2023-54034, CVE-2023-54035, CVE-2023-54036, CVE-2023-54037, CVE-2023-54038, CVE-2023-54039, CVE-2023-54040, CVE-2023-54041, CVE-2023-54042, CVE-2023-54043, CVE-2023-54044, CVE-2023-54045, CVE-2023-54046, CVE-2023-54047, CVE-2023-54048, CVE-2023-54049, CVE-2023-54050, CVE-2023-54051, CVE-2023-54052, CVE-2023-54053, CVE-2023-54055, CVE-2023-54056, CVE-2023-54057, CVE-2023-54058, CVE-2023-54059, CVE-2023-54060, CVE-2023-54062, CVE-2023-54063, CVE-2023-54064, CVE-2023-54065, CVE-2023-54066, CVE-2023-54067, CVE-2023-54068, CVE-2023-54069, CVE-2023-54070, CVE-2023-54071, CVE-2023-54072, CVE-2023-54073, CVE-2023-54074, CVE-2023-54075, CVE-2023-54076, CVE-2023-54077, CVE-2023-54078, CVE-2023-54079, CVE-2023-54080, CVE-2023-54081, CVE-2023-54083, CVE-2023-54084, CVE-2023-54085, CVE-2023-54086, CVE-2023-54087, CVE-2023-54088, CVE-2023-54089, CVE-2023-54090, CVE-2023-54091, CVE-2023-54092, CVE-2023-54093, CVE-2023-54094, CVE-2023-54095, CVE-2023-54096, CVE-2023-54097, CVE-2023-54098, CVE-2023-54099, CVE-2023-54100, CVE-2023-54101, CVE-2023-54102, CVE-2023-54104, CVE-2023-54105, CVE-2023-54106, CVE-2023-54107, CVE-2023-54108, CVE-2023-54109, CVE-2023-54110, CVE-2023-54111, CVE-2023-54112, CVE-2023-54113, CVE-2023-54114, CVE-2023-54115, CVE-2023-54116, CVE-2023-54117, CVE-2023-54118, CVE-2023-54119, CVE-2023-54120, CVE-2023-54121, CVE-2023-54122, CVE-2023-54123, CVE-2023-54124, CVE-2023-54125, CVE-2023-54126, CVE-2023-54127, CVE-2023-54128, CVE-2023-54129, CVE-2023-54130, CVE-2023-54131, CVE-2023-54132, CVE-2023-54133, CVE-2023-54134, CVE-2023-54135, CVE-2023-54136, CVE-2023-54137, CVE-2023-54138, CVE-2023-54139, CVE-2023-54140, CVE-2023-54141, CVE-2023-54142, CVE-2023-54143, CVE-2023-54144, CVE-2023-54145, CVE-2023-54146, CVE-2023-54147, CVE-2023-54148, CVE-2023-54149, CVE-2023-54150, CVE-2023-54151, CVE-2023-54152, CVE-2023-54153, CVE-2023-54154, CVE-2023-54155, CVE-2023-54156, CVE-2023-54157, CVE-2023-54158, CVE-2023-54159, CVE-2023-54160, CVE-2023-54162, CVE-2023-54164, CVE-2023-54165, CVE-2023-54166, CVE-2023-54167, CVE-2023-54168, CVE-2023-54169, CVE-2023-54170, CVE-2023-54171, CVE-2023-54172, CVE-2023-54173, CVE-2023-54174, CVE-2023-54175, CVE-2023-54176, CVE-2023-54177, CVE-2023-54178, CVE-2023-54179, CVE-2023-54180, CVE-2023-54181, CVE-2023-54182, CVE-2023-54183, CVE-2023-54184, CVE-2023-54185, CVE-2023-54186, CVE-2023-54187, CVE-2023-54188, CVE-2023-54189, CVE-2023-54190, CVE-2023-54191, CVE-2023-54192, CVE-2023-54193, CVE-2023-54194, CVE-2023-54195, CVE-2023-54196, CVE-2023-54197, CVE-2023-54198, CVE-2023-54199, CVE-2023-54200, CVE-2023-54201, CVE-2023-54202, CVE-2023-54203, CVE-2023-54204, CVE-2023-54205, CVE-2023-54206, CVE-2023-54207, CVE-2023-54208, CVE-2023-54209, CVE-2023-54210, CVE-2023-54211, CVE-2023-54213, CVE-2023-54214, CVE-2023-54215, CVE-2023-54216, CVE-2023-54217, CVE-2023-54218, CVE-2023-54219, CVE-2023-54220, CVE-2023-54221, CVE-2023-54222, CVE-2023-54223, CVE-2023-54224, CVE-2023-54225, CVE-2023-

54226, CVE-2023-54227, CVE-2023-54228, CVE-2023-54229, CVE-2023-54230, CVE-2023-54231, CVE-2023-54232, CVE-2023-54233, CVE-2023-54234, CVE-2023-54235, CVE-2023-54236, CVE-2023-54237, CVE-2023-54238, CVE-2023-54239, CVE-2023-54240, CVE-2023-54241, CVE-2023-54242, CVE-2023-54243, CVE-2023-54244, CVE-2023-54245, CVE-2023-54246, CVE-2023-54247, CVE-2023-54248, CVE-2023-54249, CVE-2023-54250, CVE-2023-54251, CVE-2023-54252, CVE-2023-54253, CVE-2023-54254, CVE-2023-54255, CVE-2023-54257, CVE-2023-54258, CVE-2023-54259, CVE-2023-54260, CVE-2023-54261, CVE-2023-54262, CVE-2023-54263, CVE-2023-54264, CVE-2023-54265, CVE-2023-54266, CVE-2023-54267, CVE-2023-54268, CVE-2023-54269, CVE-2023-54270, CVE-2023-54271, CVE-2023-54272, CVE-2023-54273, CVE-2023-54274, CVE-2023-54275, CVE-2023-54276, CVE-2023-54277, CVE-2023-54278, CVE-2023-54279, CVE-2023-54280, CVE-2023-54281, CVE-2023-54282, CVE-2023-54283, CVE-2023-54284, CVE-2023-54285, CVE-2023-54286, CVE-2023-54287, CVE-2023-54288, CVE-2023-54289, CVE-2023-54291, CVE-2023-54292, CVE-2023-54293, CVE-2023-54294, CVE-2023-54295, CVE-2023-54296, CVE-2023-54297, CVE-2023-54298, CVE-2023-54299, CVE-2023-54300, CVE-2023-54301, CVE-2023-54302, CVE-2023-54303, CVE-2023-54304, CVE-2023-54305, CVE-2023-54306, CVE-2023-54307, CVE-2023-54308, CVE-2023-54309, CVE-2023-54310, CVE-2023-54311, CVE-2023-54312, CVE-2023-54313, CVE-2023-54314, CVE-2023-54315, CVE-2023-54316, CVE-2023-54317, CVE-2023-54318, CVE-2023-54319, CVE-2023-54320, CVE-2023-54321, CVE-2023-54322, CVE-2023-54323, CVE-2023-54324, CVE-2023-54325, CVE-2023-54326, CVE-2024-26596, CVE-2024-26655, CVE-2024-26658, CVE-2024-26686, CVE-2024-26699, CVE-2024-26784, CVE-2024-26785, CVE-2024-26797, CVE-2024-26806, CVE-2024-26810, CVE-2024-26811, CVE-2024-26812, CVE-2024-26813, CVE-2024-26814, CVE-2024-26815, CVE-2024-26816, CVE-2024-26817, CVE-2024-26818, CVE-2024-26820, CVE-2024-26822, CVE-2024-26823, CVE-2024-26824, CVE-2024-26825, CVE-2024-26826, CVE-2024-26828, CVE-2024-26829, CVE-2024-26830, CVE-2024-26831, CVE-2024-26832, CVE-2024-26833, CVE-2024-26834, CVE-2024-26835, CVE-2024-26836, CVE-2024-26837, CVE-2024-26838, CVE-2024-26839, CVE-2024-26840, CVE-2024-26841, CVE-2024-26842, CVE-2024-26843, CVE-2024-26844, CVE-2024-26845, CVE-2024-26846, CVE-2024-26847, CVE-2024-26849, CVE-2024-26850, CVE-2024-26851, CVE-2024-26852, CVE-2024-26853, CVE-2024-26854, CVE-2024-26855, CVE-2024-26856, CVE-2024-26857, CVE-2024-26858, CVE-2024-26859, CVE-2024-26860, CVE-2024-26861, CVE-2024-26862, CVE-2024-26863, CVE-2024-26864, CVE-2024-26865, CVE-2024-26866, CVE-2024-26867, CVE-2024-26868, CVE-2024-26869, CVE-2024-26870, CVE-2024-26871, CVE-2024-26872, CVE-2024-26873, CVE-2024-26874, CVE-2024-26875, CVE-2024-26876, CVE-2024-26877, CVE-2024-26878, CVE-2024-26879, CVE-2024-26880, CVE-2024-26881, CVE-2024-26882, CVE-2024-26883, CVE-2024-26884, CVE-2024-26885, CVE-2024-26886, CVE-2024-26887, CVE-2024-26888, CVE-2024-26889, CVE-2024-26890, CVE-2024-26891, CVE-2024-26892, CVE-2024-26893, CVE-2024-26894, CVE-2024-26895, CVE-2024-26896, CVE-2024-26897, CVE-2024-26898, CVE-2024-26899, CVE-2024-26900, CVE-2024-26901, CVE-2024-26902, CVE-2024-26903, CVE-2024-26906, CVE-2024-26907, CVE-2024-26909, CVE-2024-26910, CVE-2024-26911, CVE-2024-26912, CVE-2024-26915, CVE-2024-26916, CVE-2024-26917, CVE-2024-26918, CVE-2024-26919, CVE-2024-26920, CVE-2024-26921, CVE-2024-26922, CVE-2024-26923, CVE-2024-26924, CVE-2024-26925, CVE-2024-26926, CVE-2024-26927, CVE-2024-26928, CVE-2024-26930, CVE-2024-26931, CVE-2024-26932, CVE-2024-26933, CVE-2024-26934, CVE-2024-26935, CVE-2024-26936, CVE-2024-26937, CVE-2024-26938, CVE-2024-26939, CVE-2024-26940, CVE-2024-26941, CVE-2024-26942, CVE-2024-26943, CVE-2024-26945, CVE-2024-26946, CVE-2024-26947, CVE-2024-26949, CVE-2024-26950, CVE-2024-26951, CVE-2024-26952, CVE-2024-26953, CVE-2024-26954, CVE-2024-26955, CVE-2024-26956, CVE-2024-26957, CVE-2024-26958, CVE-2024-26959, CVE-2024-26960, CVE-2024-26961,

CVE-2024-26962, CVE-2024-26963, CVE-2024-26964, CVE-2024-26965, CVE-2024-26966, CVE-2024-26967, CVE-2024-26968, CVE-2024-26969, CVE-2024-26970, CVE-2024-26971, CVE-2024-26973, CVE-2024-26974, CVE-2024-26975, CVE-2024-26976, CVE-2024-26977, CVE-2024-26978, CVE-2024-26980, CVE-2024-26981, CVE-2024-26982, CVE-2024-26983, CVE-2024-26984, CVE-2024-26985, CVE-2024-26986, CVE-2024-26987, CVE-2024-26988, CVE-2024-26989, CVE-2024-26990, CVE-2024-26991, CVE-2024-26992, CVE-2024-26993, CVE-2024-26994, CVE-2024-26995, CVE-2024-26996, CVE-2024-26997, CVE-2024-26998, CVE-2024-26999, CVE-2024-27000, CVE-2024-27001, CVE-2024-27002, CVE-2024-27003, CVE-2024-27004, CVE-2024-27005, CVE-2024-27006, CVE-2024-27007, CVE-2024-27008, CVE-2024-27009, CVE-2024-27011, CVE-2024-27013, CVE-2024-27014, CVE-2024-27015, CVE-2024-27016, CVE-2024-27017, CVE-2024-27018, CVE-2024-27019, CVE-2024-27020, CVE-2024-27021, CVE-2024-27023, CVE-2024-27024, CVE-2024-27025, CVE-2024-27026, CVE-2024-27027, CVE-2024-27028, CVE-2024-27029, CVE-2024-27030, CVE-2024-27031, CVE-2024-27032, CVE-2024-27033, CVE-2024-27034, CVE-2024-27035, CVE-2024-27036, CVE-2024-27037, CVE-2024-27038, CVE-2024-27039, CVE-2024-27040, CVE-2024-27041, CVE-2024-27043, CVE-2024-27044, CVE-2024-27045, CVE-2024-27046, CVE-2024-27047, CVE-2024-27048, CVE-2024-27049, CVE-2024-27050, CVE-2024-27051, CVE-2024-27052, CVE-2024-27053, CVE-2024-27054, CVE-2024-27056 and CVE-2024-27057

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2024-27058, CVE-2024-27059, CVE-2024-27060, CVE-2024-27061, CVE-2024-27062, CVE-2024-27063, CVE-2024-27064, CVE-2024-27065, CVE-2024-27066, CVE-2024-27067, CVE-2024-27068, CVE-2024-27069, CVE-2024-27070, CVE-2024-27071, CVE-2024-27072, CVE-2024-27073, CVE-2024-27074, CVE-2024-27075, CVE-2024-27076, CVE-2024-27077, CVE-2024-27078, CVE-2024-27080, CVE-2024-27388, CVE-2024-27389, CVE-2024-27390, CVE-2024-27391, CVE-2024-27392, CVE-2024-27393, CVE-2024-27394, CVE-2024-27395, CVE-2024-27396, CVE-2024-27397, CVE-2024-27398, CVE-2024-27399, CVE-2024-27400, CVE-2024-27401, CVE-2024-27402, CVE-2024-27403, CVE-2024-27404, CVE-2024-27405, CVE-2024-27406, CVE-2024-27407, CVE-2024-27408, CVE-2024-27409, CVE-2024-27410, CVE-2024-27411, CVE-2024-27412, CVE-2024-27413, CVE-2024-27414, CVE-2024-27415, CVE-2024-27416, CVE-2024-27417, CVE-2024-27418, CVE-2024-27419, CVE-2024-27431, CVE-2024-27432, CVE-2024-27433, CVE-2024-27434, CVE-2024-27435, CVE-2024-27436, CVE-2024-27437, CVE-2024-31076, CVE-2024-32936, CVE-2024-33619, CVE-2024-33621, CVE-2024-33847, CVE-2024-34027, CVE-2024-34030, CVE-2024-34777, CVE-2024-35247, CVE-2024-35784, CVE-2024-35785, CVE-2024-35786, CVE-2024-35787, CVE-2024-35789, CVE-2024-35790, CVE-2024-35791, CVE-2024-35792, CVE-2024-35793, CVE-2024-35795, CVE-2024-35796, CVE-2024-35797, CVE-2024-35798, CVE-2024-35799, CVE-2024-35800, CVE-2024-35801, CVE-2024-35803, CVE-2024-35804, CVE-2024-35805, CVE-2024-35806, CVE-2024-35807, CVE-2024-35809, CVE-2024-35810, CVE-2024-35811, CVE-2024-35813, CVE-2024-35814, CVE-2024-35815, CVE-2024-35816, CVE-2024-35817, CVE-2024-35818, CVE-2024-35819, CVE-2024-35821, CVE-2024-35822, CVE-2024-35823, CVE-2024-35824, CVE-2024-35825, CVE-2024-35826, CVE-2024-35827, CVE-2024-35828, CVE-2024-35829, CVE-2024-35830, CVE-2024-35831, CVE-2024-35832, CVE-2024-35833, CVE-2024-35834, CVE-2024-35835, CVE-2024-35836, CVE-2024-35837, CVE-2024-35838, CVE-2024-35839, CVE-2024-35840, CVE-2024-35841, CVE-2024-35842, CVE-2024-35844, CVE-2024-35845, CVE-2024-35846, CVE-2024-35847, CVE-2024-35848, CVE-2024-35849, CVE-2024-35850, CVE-2024-35851, CVE-2024-35852, CVE-2024-35853, CVE-2024-35854, CVE-2024-35855, CVE-2024-35856, CVE-2024-35857, CVE-2024-35858, CVE-2024-35859, CVE-2024-35860, CVE-2024-35861, CVE-2024-35862, CVE-2024-35863, CVE-2024-35864, CVE-2024-35865, CVE-2024-35866, CVE-2024-35867,

[illegible]

36963, CVE-2024-36964, CVE-2024-36965, CVE-2024-36966, CVE-2024-36967, CVE-2024-36968, CVE-2024-36969, CVE-2024-36970, CVE-2024-36971, CVE-2024-36972, CVE-2024-36973, CVE-2024-36974, CVE-2024-36975, CVE-2024-36976, CVE-2024-36977, CVE-2024-36978, CVE-2024-36979, CVE-2024-37021, CVE-2024-37026, CVE-2024-37078, CVE-2024-37354, CVE-2024-37356, CVE-2024-38306, CVE-2024-38381, CVE-2024-38384, CVE-2024-38385, CVE-2024-38388, CVE-2024-38390, CVE-2024-38538, CVE-2024-38539, CVE-2024-38540, CVE-2024-38541, CVE-2024-38542, CVE-2024-38543, CVE-2024-38544, CVE-2024-38545, CVE-2024-38546, CVE-2024-38547, CVE-2024-38548, CVE-2024-38549, CVE-2024-38550, CVE-2024-38551, CVE-2024-38552, CVE-2024-38553, CVE-2024-38554, CVE-2024-38555, CVE-2024-38556, CVE-2024-38557, CVE-2024-38558, CVE-2024-38559, CVE-2024-38560, CVE-2024-38561, CVE-2024-38562, CVE-2024-38563, CVE-2024-38564, CVE-2024-38565, CVE-2024-38566, CVE-2024-38567, CVE-2024-38568, CVE-2024-38569, CVE-2024-38570, CVE-2024-38571, CVE-2024-38572, CVE-2024-38573, CVE-2024-38574, CVE-2024-38575, CVE-2024-38576, CVE-2024-38577, CVE-2024-38578, CVE-2024-38579, CVE-2024-38580, CVE-2024-38581, CVE-2024-38582, CVE-2024-38583, CVE-2024-38584, CVE-2024-38585, CVE-2024-38586, CVE-2024-38587, CVE-2024-38588, CVE-2024-38589, CVE-2024-38590, CVE-2024-38591, CVE-2024-38592, CVE-2024-38593, CVE-2024-38594, CVE-2024-38595, CVE-2024-38596, CVE-2024-38597, CVE-2024-38598, CVE-2024-38599, CVE-2024-38600, CVE-2024-38601, CVE-2024-38602, CVE-2024-38603, CVE-2024-38604, CVE-2024-38605, CVE-2024-38606, CVE-2024-38607, CVE-2024-38609, CVE-2024-38610, CVE-2024-38611, CVE-2024-38612, CVE-2024-38613, CVE-2024-38614, CVE-2024-38615, CVE-2024-38616, CVE-2024-38617, CVE-2024-38618, CVE-2024-38619, CVE-2024-38620, CVE-2024-38621, CVE-2024-38622, CVE-2024-38623, CVE-2024-38624, CVE-2024-38625, CVE-2024-38626, CVE-2024-38627, CVE-2024-38628, CVE-2024-38629, CVE-2024-38630, CVE-2024-38631, CVE-2024-38632, CVE-2024-38633, CVE-2024-38634, CVE-2024-38635, CVE-2024-38636, CVE-2024-38637, CVE-2024-38659, CVE-2024-38661, CVE-2024-38662, CVE-2024-38663, CVE-2024-38664, CVE-2024-38667, CVE-2024-38780, CVE-2024-39276, CVE-2024-39277, CVE-2024-39282, CVE-2024-39291 and CVE-2024-39292

- **linux-yocto/6.6: (Cont.)** Ignore CVE-2024-39293, CVE-2024-39296, CVE-2024-39298, CVE-2024-39301, CVE-2024-39371, CVE-2024-39461, CVE-2024-39462, CVE-2024-39463, CVE-2024-39464, CVE-2024-39465, CVE-2024-39466, CVE-2024-39467, CVE-2024-39468, CVE-2024-39469, CVE-2024-39470, CVE-2024-39471, CVE-2024-39472, CVE-2024-39473, CVE-2024-39474, CVE-2024-39475, CVE-2024-39476, CVE-2024-39477, CVE-2024-39479, CVE-2024-39480, CVE-2024-39481, CVE-2024-39482, CVE-2024-39483, CVE-2024-39484, CVE-2024-39485, CVE-2024-39486, CVE-2024-39487, CVE-2024-39488, CVE-2024-39489, CVE-2024-39490, CVE-2024-39491, CVE-2024-39492, CVE-2024-39493, CVE-2024-39494, CVE-2024-39495, CVE-2024-39496, CVE-2024-39497, CVE-2024-39498, CVE-2024-39499, CVE-2024-39500, CVE-2024-39502, CVE-2024-39503, CVE-2024-39504, CVE-2024-39505, CVE-2024-39506, CVE-2024-39507, CVE-2024-39508, CVE-2024-39509, CVE-2024-39510, CVE-2024-40899, CVE-2024-40900, CVE-2024-40901, CVE-2024-40902, CVE-2024-40903, CVE-2024-40904, CVE-2024-40905, CVE-2024-40906, CVE-2024-40907, CVE-2024-40908, CVE-2024-40909, CVE-2024-40910, CVE-2024-40911, CVE-2024-40912, CVE-2024-40913, CVE-2024-40914, CVE-2024-40915, CVE-2024-40916, CVE-2024-40917, CVE-2024-40918, CVE-2024-40919, CVE-2024-40920, CVE-2024-40921, CVE-2024-40922, CVE-2024-40923, CVE-2024-40924, CVE-2024-40925, CVE-2024-40926, CVE-2024-40927, CVE-2024-40928, CVE-2024-40929, CVE-2024-40930, CVE-2024-40931, CVE-2024-40932, CVE-2024-40933, CVE-2024-40934, CVE-2024-40935, CVE-2024-40936, CVE-2024-40937, CVE-2024-40938, CVE-2024-40939, CVE-2024-40940, CVE-2024-40941, CVE-2024-40942, CVE-2024-

[illegible]



CVE-2024-42237, CVE-2024-42238, CVE-2024-42239, CVE-2024-42240, CVE-2024-42241, CVE-2024-42242, CVE-2024-42243, CVE-2024-42244, CVE-2024-42245, CVE-2024-42246, CVE-2024-42247, CVE-2024-42248, CVE-2024-42249, CVE-2024-42250, CVE-2024-42251, CVE-2024-42252, CVE-2024-42253, CVE-2024-42254, CVE-2024-42255, CVE-2024-42256, CVE-2024-42257, CVE-2024-42259, CVE-2024-42260, CVE-2024-42261, CVE-2024-42262, CVE-2024-42263, CVE-2024-42264, CVE-2024-42265, CVE-2024-42266, CVE-2024-42267, CVE-2024-42268, CVE-2024-42269, CVE-2024-42270, CVE-2024-42271, CVE-2024-42272, CVE-2024-42273, CVE-2024-42274, CVE-2024-42275, CVE-2024-42276, CVE-2024-42277, CVE-2024-42278, CVE-2024-42279, CVE-2024-42280, CVE-2024-42281, CVE-2024-42282, CVE-2024-42283, CVE-2024-42284, CVE-2024-42285, CVE-2024-42286, CVE-2024-42287, CVE-2024-42288, CVE-2024-42289, CVE-2024-42290, CVE-2024-42291, CVE-2024-42292, CVE-2024-42293, CVE-2024-42294, CVE-2024-42295, CVE-2024-42296, CVE-2024-42297, CVE-2024-42298, CVE-2024-42299, CVE-2024-42300, CVE-2024-42301, CVE-2024-42302, CVE-2024-42303, CVE-2024-42304, CVE-2024-42305, CVE-2024-42306, CVE-2024-42307, CVE-2024-42309, CVE-2024-42310, CVE-2024-42311, CVE-2024-42312, CVE-2024-42313, CVE-2024-42314, CVE-2024-42315, CVE-2024-42316, CVE-2024-42318, CVE-2024-42319, CVE-2024-42320, CVE-2024-42321, CVE-2024-42322, CVE-2024-43098, CVE-2024-43815, CVE-2024-43816, CVE-2024-43817, CVE-2024-43818, CVE-2024-43820, CVE-2024-43821, CVE-2024-43822, CVE-2024-43823, CVE-2024-43825, CVE-2024-43827, CVE-2024-43828, CVE-2024-43829, CVE-2024-43830, CVE-2024-43831, CVE-2024-43832, CVE-2024-43833, CVE-2024-43834, CVE-2024-43835, CVE-2024-43836, CVE-2024-43837, CVE-2024-43838, CVE-2024-43839, CVE-2024-43840, CVE-2024-43841, CVE-2024-43842, CVE-2024-43843, CVE-2024-43844, CVE-2024-43845, CVE-2024-43846, CVE-2024-43847, CVE-2024-43848, CVE-2024-43849, CVE-2024-43850, CVE-2024-43851, CVE-2024-43852, CVE-2024-43853, CVE-2024-43854, CVE-2024-43855, CVE-2024-43856, CVE-2024-43857, CVE-2024-43858, CVE-2024-43859, CVE-2024-43860, CVE-2024-43861, CVE-2024-43862, CVE-2024-43863, CVE-2024-43864, CVE-2024-43865, CVE-2024-43866, CVE-2024-43867, CVE-2024-43868, CVE-2024-43869, CVE-2024-43870, CVE-2024-43871, CVE-2024-43873, CVE-2024-43874, CVE-2024-43875, CVE-2024-43876, CVE-2024-43877, CVE-2024-43878, CVE-2024-43879, CVE-2024-43880, CVE-2024-43881, CVE-2024-43882, CVE-2024-43883, CVE-2024-43884, CVE-2024-43886, CVE-2024-43887, CVE-2024-43888, CVE-2024-43889, CVE-2024-43890, CVE-2024-43891, CVE-2024-43892, CVE-2024-43893, CVE-2024-43894, CVE-2024-43896, CVE-2024-43897, CVE-2024-43899, CVE-2024-43900, CVE-2024-43902, CVE-2024-43904, CVE-2024-43905, CVE-2024-43906, CVE-2024-43907, CVE-2024-43908, CVE-2024-43909, CVE-2024-43910, CVE-2024-43911, CVE-2024-43912, CVE-2024-43913, CVE-2024-43914, CVE-2024-44931, CVE-2024-44932, CVE-2024-44933, CVE-2024-44934, CVE-2024-44935, CVE-2024-44936, CVE-2024-44937, CVE-2024-44938, CVE-2024-44939, CVE-2024-44940, CVE-2024-44941, CVE-2024-44942 and CVE-2024-44943

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2024-44944, CVE-2024-44945, CVE-2024-44946, CVE-2024-44947, CVE-2024-44948, CVE-2024-44949, CVE-2024-44950, CVE-2024-44951, CVE-2024-44953, CVE-2024-44954, CVE-2024-44956, CVE-2024-44957, CVE-2024-44958, CVE-2024-44959, CVE-2024-44960, CVE-2024-44961, CVE-2024-44962, CVE-2024-44963, CVE-2024-44964, CVE-2024-44965, CVE-2024-44966, CVE-2024-44967, CVE-2024-44968, CVE-2024-44969, CVE-2024-44970, CVE-2024-44971, CVE-2024-44973, CVE-2024-44974, CVE-2024-44975, CVE-2024-44976, CVE-2024-44977, CVE-2024-44978, CVE-2024-44979, CVE-2024-44980, CVE-2024-44981, CVE-2024-44982, CVE-2024-44983, CVE-2024-44984, CVE-2024-44985, CVE-2024-44986, CVE-2024-44987, CVE-2024-44988, CVE-2024-44989, CVE-2024-44990, CVE-2024-44991, CVE-2024-44992, CVE-2024-44993, CVE-2024-44994,

[illegible]



## 17.7. Release 5.0 (scarthgap) 1441



17.7. Release 5.0 (scarthgap) 1443

CVE-2024-56547, CVE-2024-56548, CVE-2024-56549, CVE-2024-56550, CVE-2024-56551, CVE-2024-56552, CVE-2024-56553, CVE-2024-56554, CVE-2024-56555, CVE-2024-56556, CVE-2024-56557, CVE-2024-56558, CVE-2024-56559, CVE-2024-56560, CVE-2024-56561, CVE-2024-56562, CVE-2024-56563, CVE-2024-56564, CVE-2024-56565, CVE-2024-56566, CVE-2024-56567, CVE-2024-56568, CVE-2024-56569, CVE-2024-56570, CVE-2024-56572, CVE-2024-56573, CVE-2024-56574, CVE-2024-56575, CVE-2024-56576, CVE-2024-56577, CVE-2024-56578, CVE-2024-56579, CVE-2024-56580, CVE-2024-56581, CVE-2024-56582, CVE-2024-56583, CVE-2024-56584, CVE-2024-56585, CVE-2024-56586 and CVE-2024-56587

- **linux-yocto/6.6: (Cont.)** Ignore CVE-2024-56588, CVE-2024-56589, CVE-2024-56590, CVE-2024-56592, CVE-2024-56593, CVE-2024-56594, CVE-2024-56595, CVE-2024-56596, CVE-2024-56597, CVE-2024-56598, CVE-2024-56599, CVE-2024-56600, CVE-2024-56601, CVE-2024-56602, CVE-2024-56603, CVE-2024-56604, CVE-2024-56605, CVE-2024-56606, CVE-2024-56607, CVE-2024-56608, CVE-2024-56609, CVE-2024-56610, CVE-2024-56611, CVE-2024-56612, CVE-2024-56613, CVE-2024-56614, CVE-2024-56615, CVE-2024-56616, CVE-2024-56617, CVE-2024-56618, CVE-2024-56619, CVE-2024-56620, CVE-2024-56621, CVE-2024-56622, CVE-2024-56623, CVE-2024-56624, CVE-2024-56625, CVE-2024-56626, CVE-2024-56627, CVE-2024-56628, CVE-2024-56629, CVE-2024-56630, CVE-2024-56631, CVE-2024-56632, CVE-2024-56633, CVE-2024-56634, CVE-2024-56635, CVE-2024-56636, CVE-2024-56637, CVE-2024-56638, CVE-2024-56639, CVE-2024-56640, CVE-2024-56641, CVE-2024-56642, CVE-2024-56643, CVE-2024-56644, CVE-2024-56645, CVE-2024-56646, CVE-2024-56648, CVE-2024-56649, CVE-2024-56650, CVE-2024-56651, CVE-2024-56652, CVE-2024-56653, CVE-2024-56654, CVE-2024-56655, CVE-2024-56656, CVE-2024-56657, CVE-2024-56658, CVE-2024-56659, CVE-2024-56660, CVE-2024-56661, CVE-2024-56662, CVE-2024-56663, CVE-2024-56664, CVE-2024-56665, CVE-2024-56666, CVE-2024-56667, CVE-2024-56668, CVE-2024-56669, CVE-2024-56670, CVE-2024-56671, CVE-2024-56672, CVE-2024-56673, CVE-2024-56674, CVE-2024-56675, CVE-2024-56676, CVE-2024-56677, CVE-2024-56678, CVE-2024-56679, CVE-2024-56680, CVE-2024-56681, CVE-2024-56682, CVE-2024-56683, CVE-2024-56684, CVE-2024-56685, CVE-2024-56687, CVE-2024-56688, CVE-2024-56689, CVE-2024-56690, CVE-2024-56691, CVE-2024-56692, CVE-2024-56693, CVE-2024-56694, CVE-2024-56695, CVE-2024-56696, CVE-2024-56697, CVE-2024-56698, CVE-2024-56699, CVE-2024-56700, CVE-2024-56701, CVE-2024-56703, CVE-2024-56704, CVE-2024-56705, CVE-2024-56706, CVE-2024-56707, CVE-2024-56708, CVE-2024-56709, CVE-2024-56710, CVE-2024-56711, CVE-2024-56713, CVE-2024-56714, CVE-2024-56715, CVE-2024-56716, CVE-2024-56717, CVE-2024-56718, CVE-2024-56719, CVE-2024-56720, CVE-2024-56721, CVE-2024-56722, CVE-2024-56723, CVE-2024-56724, CVE-2024-56725, CVE-2024-56726, CVE-2024-56727, CVE-2024-56728, CVE-2024-56729, CVE-2024-56730, CVE-2024-56739, CVE-2024-56740, CVE-2024-56743, CVE-2024-56744, CVE-2024-56745, CVE-2024-56746, CVE-2024-56747, CVE-2024-56748, CVE-2024-56749, CVE-2024-56750, CVE-2024-56751, CVE-2024-56752, CVE-2024-56753, CVE-2024-56754, CVE-2024-56755, CVE-2024-56756, CVE-2024-56757, CVE-2024-56758, CVE-2024-56759, CVE-2024-56760, CVE-2024-56761, CVE-2024-56763, CVE-2024-56764, CVE-2024-56765, CVE-2024-56766, CVE-2024-56767, CVE-2024-56768, CVE-2024-56769, CVE-2024-56770, CVE-2024-56771, CVE-2024-56772, CVE-2024-56773, CVE-2024-56774, CVE-2024-56776, CVE-2024-56777, CVE-2024-56778, CVE-2024-56779, CVE-2024-56780, CVE-2024-56782, CVE-2024-56783, CVE-2024-56784, CVE-2024-56785, CVE-2024-56787, CVE-2024-56788, CVE-2024-57791, CVE-2024-57792, CVE-2024-57793, CVE-2024-57795, CVE-2024-57798, CVE-2024-57799, CVE-2024-57800, CVE-2024-57801, CVE-2024-57802, CVE-2024-57805, CVE-2024-57806, CVE-2024-57807, CVE-2024-57834, CVE-2024-57838, CVE-2024-

17.7. Release 5.0 (scarthgap) 1445

CVE-2025-21710, CVE-2025-21711, CVE-2025-21712, CVE-2025-21713, CVE-2025-21715, CVE-2025-21716, CVE-2025-21717, CVE-2025-21718, CVE-2025-21719, CVE-2025-21720, CVE-2025-21721, CVE-2025-21724, CVE-2025-21725, CVE-2025-21726, CVE-2025-21727, CVE-2025-21728, CVE-2025-21730, CVE-2025-21731, CVE-2025-21733, CVE-2025-21734, CVE-2025-21735, CVE-2025-21736, CVE-2025-21737, CVE-2025-21738, CVE-2025-21741, CVE-2025-21742, CVE-2025-21743, CVE-2025-21744, CVE-2025-21745, CVE-2025-21746, CVE-2025-21747, CVE-2025-21748, CVE-2025-21749, CVE-2025-21750, CVE-2025-21751, CVE-2025-21752, CVE-2025-21753, CVE-2025-21754, CVE-2025-21756, CVE-2025-21758, CVE-2025-21759, CVE-2025-21760, CVE-2025-21761, CVE-2025-21762, CVE-2025-21763, CVE-2025-21764, CVE-2025-21765, CVE-2025-21766, CVE-2025-21767, CVE-2025-21769, CVE-2025-21770, CVE-2025-21771, CVE-2025-21772, CVE-2025-21773, CVE-2025-21774, CVE-2025-21775, CVE-2025-21776, CVE-2025-21777, CVE-2025-21778, CVE-2025-21779, CVE-2025-21780, CVE-2025-21781, CVE-2025-21782, CVE-2025-21783, CVE-2025-21784, CVE-2025-21785, CVE-2025-21786, CVE-2025-21787, CVE-2025-21788, CVE-2025-21789, CVE-2025-21790, CVE-2025-21791, CVE-2025-21792, CVE-2025-21793, CVE-2025-21794, CVE-2025-21795, CVE-2025-21796, CVE-2025-21797, CVE-2025-21798, CVE-2025-21799, CVE-2025-21800, CVE-2025-21802, CVE-2025-21803, CVE-2025-21804, CVE-2025-21805, CVE-2025-21806, CVE-2025-21807, CVE-2025-21808 and CVE-2025-21809

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2025-21810, CVE-2025-21811, CVE-2025-21812, CVE-2025-21813, CVE-2025-21814, CVE-2025-21815, CVE-2025-21816, CVE-2025-21817, CVE-2025-21819, CVE-2025-21820, CVE-2025-21821, CVE-2025-21822, CVE-2025-21823, CVE-2025-21824, CVE-2025-21826, CVE-2025-21827, CVE-2025-21828, CVE-2025-21829, CVE-2025-21830, CVE-2025-21831, CVE-2025-21832, CVE-2025-21833, CVE-2025-21834, CVE-2025-21835, CVE-2025-21836, CVE-2025-21838, CVE-2025-21839, CVE-2025-21840, CVE-2025-21841, CVE-2025-21842, CVE-2025-21843, CVE-2025-21844, CVE-2025-21845, CVE-2025-21846, CVE-2025-21847, CVE-2025-21848, CVE-2025-21849, CVE-2025-21850, CVE-2025-21851, CVE-2025-21852, CVE-2025-21853, CVE-2025-21854, CVE-2025-21855, CVE-2025-21856, CVE-2025-21857, CVE-2025-21858, CVE-2025-21859, CVE-2025-21860, CVE-2025-21861, CVE-2025-21862, CVE-2025-21863, CVE-2025-21864, CVE-2025-21865, CVE-2025-21866, CVE-2025-21867, CVE-2025-21868, CVE-2025-21869, CVE-2025-21871, CVE-2025-21872, CVE-2025-21873, CVE-2025-21874, CVE-2025-21875, CVE-2025-21876, CVE-2025-21877, CVE-2025-21878, CVE-2025-21879, CVE-2025-21880, CVE-2025-21881, CVE-2025-21882, CVE-2025-21883, CVE-2025-21884, CVE-2025-21886, CVE-2025-21887, CVE-2025-21889, CVE-2025-21890, CVE-2025-21891, CVE-2025-21893, CVE-2025-21894, CVE-2025-21895, CVE-2025-21896, CVE-2025-21897, CVE-2025-21898, CVE-2025-21899, CVE-2025-21900, CVE-2025-21901, CVE-2025-21902, CVE-2025-21903, CVE-2025-21904, CVE-2025-21905, CVE-2025-21906, CVE-2025-21908, CVE-2025-21909, CVE-2025-21910, CVE-2025-21911, CVE-2025-21912, CVE-2025-21913, CVE-2025-21914, CVE-2025-21915, CVE-2025-21916, CVE-2025-21917, CVE-2025-21918, CVE-2025-21919, CVE-2025-21920, CVE-2025-21921, CVE-2025-21922, CVE-2025-21923, CVE-2025-21924, CVE-2025-21925, CVE-2025-21926, CVE-2025-21928, CVE-2025-21929, CVE-2025-21930, CVE-2025-21931, CVE-2025-21932, CVE-2025-21933, CVE-2025-21934, CVE-2025-21935, CVE-2025-21936, CVE-2025-21937, CVE-2025-21938, CVE-2025-21939, CVE-2025-21940, CVE-2025-21941, CVE-2025-21942, CVE-2025-21943, CVE-2025-21944, CVE-2025-21945, CVE-2025-21946, CVE-2025-21947, CVE-2025-21948, CVE-2025-21950, CVE-2025-21951, CVE-2025-21952, CVE-2025-21953, CVE-2025-21954, CVE-2025-21955, CVE-2025-21956, CVE-2025-21957, CVE-2025-21958, CVE-2025-21959, CVE-2025-21960, CVE-2025-21962, CVE-2025-21963, CVE-2025-21964, CVE-2025-21965, CVE-2025-21966, CVE-2025-21967,



## 17.7. Release 5.0 (scarthgap) 1447

37819, CVE-2025-37820, CVE-2025-37821, CVE-2025-37822, CVE-2025-37823, CVE-2025-37824, CVE-2025-37825, CVE-2025-37827, CVE-2025-37828, CVE-2025-37829, CVE-2025-37830, CVE-2025-37831, CVE-2025-37836, CVE-2025-37837, CVE-2025-37838, CVE-2025-37839, CVE-2025-37840, CVE-2025-37841, CVE-2025-37842, CVE-2025-37843, CVE-2025-37844, CVE-2025-37845, CVE-2025-37846, CVE-2025-37847, CVE-2025-37848, CVE-2025-37849, CVE-2025-37850, CVE-2025-37851, CVE-2025-37852, CVE-2025-37853, CVE-2025-37854, CVE-2025-37855, CVE-2025-37857, CVE-2025-37858, CVE-2025-37859, CVE-2025-37862, CVE-2025-37863, CVE-2025-37864, CVE-2025-37865, CVE-2025-37866, CVE-2025-37867, CVE-2025-37868, CVE-2025-37869, CVE-2025-37871, CVE-2025-37872, CVE-2025-37873, CVE-2025-37874, CVE-2025-37875, CVE-2025-37876, CVE-2025-37877, CVE-2025-37878, CVE-2025-37879, CVE-2025-37881, CVE-2025-37882, CVE-2025-37883, CVE-2025-37884, CVE-2025-37885, CVE-2025-37886, CVE-2025-37887, CVE-2025-37888, CVE-2025-37889, CVE-2025-37890, CVE-2025-37891, CVE-2025-37892, CVE-2025-37893, CVE-2025-37894, CVE-2025-37895, CVE-2025-37896, CVE-2025-37897, CVE-2025-37898, CVE-2025-37899, CVE-2025-37900, CVE-2025-37901, CVE-2025-37903, CVE-2025-37904, CVE-2025-37905, CVE-2025-37906, CVE-2025-37908, CVE-2025-37909, CVE-2025-37910, CVE-2025-37911, CVE-2025-37912, CVE-2025-37913, CVE-2025-37914, CVE-2025-37915, CVE-2025-37916, CVE-2025-37917, CVE-2025-37918, CVE-2025-37919, CVE-2025-37920, CVE-2025-37921, CVE-2025-37922, CVE-2025-37923, CVE-2025-37924, CVE-2025-37925, CVE-2025-37926, CVE-2025-37927, CVE-2025-37928, CVE-2025-37929, CVE-2025-37930, CVE-2025-37931, CVE-2025-37932, CVE-2025-37933, CVE-2025-37934, CVE-2025-37935, CVE-2025-37936, CVE-2025-37937, CVE-2025-37938, CVE-2025-37939, CVE-2025-37940, CVE-2025-37941, CVE-2025-37943, CVE-2025-37944, CVE-2025-37945, CVE-2025-37946, CVE-2025-37947, CVE-2025-37948, CVE-2025-37949, CVE-2025-37950, CVE-2025-37951, CVE-2025-37952, CVE-2025-37953, CVE-2025-37954, CVE-2025-37955, CVE-2025-37956, CVE-2025-37957, CVE-2025-37958, CVE-2025-37959, CVE-2025-37960, CVE-2025-37961, CVE-2025-37962, CVE-2025-37963, CVE-2025-37964, CVE-2025-37965, CVE-2025-37966, CVE-2025-37967, CVE-2025-37968, CVE-2025-37969 and CVE-2025-37970

- **linux-yocto/6.6: (Cont.)** Ignore CVE-2025-37971, CVE-2025-37972, CVE-2025-37973, CVE-2025-37974, CVE-2025-37975, CVE-2025-37978, CVE-2025-37979, CVE-2025-37980, CVE-2025-37981, CVE-2025-37982, CVE-2025-37983, CVE-2025-37984, CVE-2025-37985, CVE-2025-37986, CVE-2025-37987, CVE-2025-37988, CVE-2025-37989, CVE-2025-37990, CVE-2025-37991, CVE-2025-37992, CVE-2025-37993, CVE-2025-37994, CVE-2025-37995, CVE-2025-37996, CVE-2025-37997, CVE-2025-37998, CVE-2025-37999, CVE-2025-38000, CVE-2025-38001, CVE-2025-38002, CVE-2025-38003, CVE-2025-38004, CVE-2025-38005, CVE-2025-38006, CVE-2025-38007, CVE-2025-38008, CVE-2025-38009, CVE-2025-38010, CVE-2025-38011, CVE-2025-38012, CVE-2025-38013, CVE-2025-38014, CVE-2025-38015, CVE-2025-38016, CVE-2025-38017, CVE-2025-38018, CVE-2025-38019, CVE-2025-38020, CVE-2025-38021, CVE-2025-38022, CVE-2025-38023, CVE-2025-38024, CVE-2025-38025, CVE-2025-38027, CVE-2025-38028, CVE-2025-38031, CVE-2025-38032, CVE-2025-38033, CVE-2025-38034, CVE-2025-38035, CVE-2025-38036, CVE-2025-38037, CVE-2025-38039, CVE-2025-38040, CVE-2025-38043, CVE-2025-38044, CVE-2025-38045, CVE-2025-38047, CVE-2025-38048, CVE-2025-38049, CVE-2025-38050, CVE-2025-38051, CVE-2025-38052, CVE-2025-38053, CVE-2025-38054, CVE-2025-38055, CVE-2025-38056, CVE-2025-38057, CVE-2025-38058, CVE-2025-38059, CVE-2025-38060, CVE-2025-38061, CVE-2025-38062, CVE-2025-38063, CVE-2025-38065, CVE-2025-38066, CVE-2025-38067, CVE-2025-38068, CVE-2025-38070, CVE-2025-38071, CVE-2025-38072, CVE-2025-38074, CVE-2025-38075, CVE-2025-38076, CVE-2025-38077, CVE-2025-38078, CVE-2025-38079, CVE-2025-



17.7. Release 5.0 (scarthgap) 1449

[illegible]

- [linux-yocto/6.6: \(Cont.\) Ignore CVE-2025-38546, CVE-2025-38547, CVE-2025-38548, CVE-2025-38549, CVE-2025-38550, CVE-2025-38551, CVE-2025-38552, CVE-2025-38553, CVE-2025-38554, CVE-2025-38555, CVE-2025-38556, CVE-2025-38557, CVE-2025-38558, CVE-2025-38559, CVE-2025-38560, CVE-2025-38561, CVE-2025-38562, CVE-2025-38563, CVE-2025-38564, CVE-2025-38565, CVE-2025-38566, CVE-2025-38567, CVE-2025-38568, CVE-2025-38569, CVE-2025-38570, CVE-2025-38571, CVE-2025-38572, CVE-2025-38573, CVE-2025-38574, CVE-2025-38575, CVE-2025-38576, CVE-2025-38577, CVE-2025-38578, CVE-2025-38579, CVE-2025-38580, CVE-2025-38581, CVE-2025-38582, CVE-2025-38583, CVE-2025-38586, CVE-2025-38587, CVE-2025-38588, CVE-2025-38589, CVE-2025-38590, CVE-2025-38592, CVE-2025-38593, CVE-2025-38594, CVE-2025-38596, CVE-2025-38598](#)

## 17.7. Release 5.0 (scarthgap) 1451

[illegible]

- 17.7. Release 5.0 (scarthgap) 1453





68781, CVE-2025-68782, CVE-2025-68783, CVE-2025-68784, CVE-2025-68785, CVE-2025-68786, CVE-2025-68787, CVE-2025-68788, CVE-2025-68790, CVE-2025-68791, CVE-2025-68792, CVE-2025-68793, CVE-2025-68794, CVE-2025-68795, CVE-2025-68796, CVE-2025-68797, CVE-2025-68798, CVE-2025-68799, CVE-2025-68800, CVE-2025-68801, CVE-2025-68802, CVE-2025-68803, CVE-2025-68804, CVE-2025-68805, CVE-2025-68806, CVE-2025-68807, CVE-2025-68808, CVE-2025-68809, CVE-2025-68810, CVE-2025-68811, CVE-2025-68812, CVE-2025-68813, CVE-2025-68814, CVE-2025-68815, CVE-2025-68816, CVE-2025-68817, CVE-2025-68818, CVE-2025-68819, CVE-2025-68820 and CVE-2025-68821

- **linux-yocto/6.6: (Cont.) Ignore** CVE-2025-71064, CVE-2025-71065, CVE-2025-71066, CVE-2025-71067, CVE-2025-71068, CVE-2025-71069, CVE-2025-71070, CVE-2025-71071, CVE-2025-71075, CVE-2025-71076, CVE-2025-71077, CVE-2025-71078, CVE-2025-71079, CVE-2025-71080, CVE-2025-71081, CVE-2025-71082, CVE-2025-71083, CVE-2025-71084, CVE-2025-71085, CVE-2025-71086, CVE-2025-71087, CVE-2025-71088, CVE-2025-71089, CVE-2025-71090, CVE-2025-71091, CVE-2025-71092, CVE-2025-71093, CVE-2025-71094, CVE-2025-71095, CVE-2025-71096, CVE-2025-71097, CVE-2025-71098, CVE-2025-71099, CVE-2025-71100, CVE-2025-71101, CVE-2025-71102, CVE-2025-71103, CVE-2025-71104, CVE-2025-71105, CVE-2025-71106, CVE-2025-71107, CVE-2025-71108, CVE-2025-71110, CVE-2025-71111, CVE-2025-71112, CVE-2025-71113, CVE-2025-71114, CVE-2025-71115, CVE-2025-71116, CVE-2025-71117, CVE-2025-71118, CVE-2025-71119, CVE-2025-71120, CVE-2025-71121, CVE-2025-71122, CVE-2025-71123, CVE-2025-71124, CVE-2025-71125, CVE-2025-71126, CVE-2025-71127, CVE-2025-71128, CVE-2025-71129, CVE-2025-71130, CVE-2025-71131, CVE-2025-71132, CVE-2025-71133, CVE-2025-71134, CVE-2025-71135, CVE-2025-71136, CVE-2025-71137, CVE-2025-71138, CVE-2025-71139, CVE-2025-71140, CVE-2025-71141, CVE-2025-71142, CVE-2025-71143, CVE-2025-71144, CVE-2025-71146, CVE-2025-71147, CVE-2025-71148, CVE-2025-71149, CVE-2025-71150, CVE-2025-71151, CVE-2025-71153, CVE-2025-71154, CVE-2025-71155, CVE-2025-71156, CVE-2025-71157, CVE-2025-71158, CVE-2025-71159, CVE-2025-71160, CVE-2025-71162, CVE-2025-71163, CVE-2025-71180, CVE-2025-71181, CVE-2025-71182, CVE-2025-71183, CVE-2025-71185, CVE-2025-71186, CVE-2025-71187, CVE-2025-71188, CVE-2025-71189, CVE-2025-71190, CVE-2025-71191, CVE-2025-71192, CVE-2025-71193, CVE-2025-71194, CVE-2025-71195, CVE-2025-71196, CVE-2025-71197, CVE-2025-71198, CVE-2025-71199, CVE-2025-71200, CVE-2025-71201, CVE-2025-71230, CVE-2025-71231, CVE-2025-71234, CVE-2026-22976, CVE-2026-22977, CVE-2026-22978, CVE-2026-22979, CVE-2026-22980, CVE-2026-22981, CVE-2026-22982, CVE-2026-22983, CVE-2026-22984, CVE-2026-22985, CVE-2026-22986, CVE-2026-22987, CVE-2026-22988, CVE-2026-22989, CVE-2026-22990, CVE-2026-22991, CVE-2026-22992, CVE-2026-22993, CVE-2026-22994, CVE-2026-22995, CVE-2026-22997, CVE-2026-22998, CVE-2026-22999, CVE-2026-23001, CVE-2026-23002, CVE-2026-23003, CVE-2026-23005, CVE-2026-23006, CVE-2026-23007, CVE-2026-23008, CVE-2026-23009, CVE-2026-23010, CVE-2026-23011, CVE-2026-23012, CVE-2026-23013, CVE-2026-23014, CVE-2026-23015, CVE-2026-23016, CVE-2026-23017, CVE-2026-23018, CVE-2026-23019, CVE-2026-23020, CVE-2026-23021, CVE-2026-23022, CVE-2026-23023, CVE-2026-23024, CVE-2026-23025, CVE-2026-23026, CVE-2026-23027, CVE-2026-23028, CVE-2026-23029, CVE-2026-23030, CVE-2026-23031, CVE-2026-23032, CVE-2026-23033, CVE-2026-23034, CVE-2026-23036, CVE-2026-23037, CVE-2026-23038, CVE-2026-23039, CVE-2026-23040, CVE-2026-23041, CVE-2026-23042, CVE-2026-23043, CVE-2026-23044, CVE-2026-23045, CVE-2026-23046, CVE-2026-23047, CVE-2026-23048, CVE-2026-23049, CVE-2026-23051, CVE-2026-23052, CVE-2026-23054, CVE-2026-23055, CVE-2026-23056, CVE-2026-23057, CVE-2026-23058, CVE-2026-23059, CVE-2026-23060,

CVE-2026-23061, CVE-2026-23062, CVE-2026-23063, CVE-2026-23064, CVE-2026-23065, CVE-2026-23067, CVE-2026-23068, CVE-2026-23069, CVE-2026-23070, CVE-2026-23071, CVE-2026-23072, CVE-2026-23073, CVE-2026-23074, CVE-2026-23075, CVE-2026-23076, CVE-2026-23077, CVE-2026-23078, CVE-2026-23079, CVE-2026-23080, CVE-2026-23081, CVE-2026-23082, CVE-2026-23083, CVE-2026-23084, CVE-2026-23085, CVE-2026-23086, CVE-2026-23087, CVE-2026-23088, CVE-2026-23089, CVE-2026-23090, CVE-2026-23091, CVE-2026-23092, CVE-2026-23093, CVE-2026-23094, CVE-2026-23095, CVE-2026-23096, CVE-2026-23097, CVE-2026-23098, CVE-2026-23099, CVE-2026-23101, CVE-2026-23102, CVE-2026-23103, CVE-2026-23104, CVE-2026-23105, CVE-2026-23106, CVE-2026-23107, CVE-2026-23108, CVE-2026-23109, CVE-2026-23110, CVE-2026-23113, CVE-2026-23114, CVE-2026-23115, CVE-2026-23116, CVE-2026-23117, CVE-2026-23119, CVE-2026-23120, CVE-2026-23121, CVE-2026-23122, CVE-2026-23123, CVE-2026-23124, CVE-2026-23125, CVE-2026-23126, CVE-2026-23127, CVE-2026-23128, CVE-2026-23129, CVE-2026-23130, CVE-2026-23131, CVE-2026-23132, CVE-2026-23133, CVE-2026-23134, CVE-2026-23135, CVE-2026-23136, CVE-2026-23139, CVE-2026-23140, CVE-2026-23141, CVE-2026-23142, CVE-2026-23143, CVE-2026-23144, CVE-2026-23145, CVE-2026-23146, CVE-2026-23147, CVE-2026-23148, CVE-2026-23149, CVE-2026-23150, CVE-2026-23151, CVE-2026-23152, CVE-2026-23153, CVE-2026-23155, CVE-2026-23156, CVE-2026-23158, CVE-2026-23159, CVE-2026-23160, CVE-2026-23161, CVE-2026-23162, CVE-2026-23163, CVE-2026-23164, CVE-2026-23165, CVE-2026-23166, CVE-2026-23167, CVE-2026-23168, CVE-2026-23170, CVE-2026-23172, CVE-2026-23173, CVE-2026-23174, CVE-2026-23175, CVE-2026-23177, CVE-2026-23179, CVE-2026-23181, CVE-2026-23183, CVE-2026-23184, CVE-2026-23185, CVE-2026-23186, CVE-2026-23188, CVE-2026-23189, CVE-2026-23192, CVE-2026-23194, CVE-2026-23195, CVE-2026-23196, CVE-2026-23197, CVE-2026-23199, CVE-2026-23201, CVE-2026-23203, CVE-2026-23207, CVE-2026-23210, CVE-2026-23211, CVE-2026-23212, CVE-2026-23215, CVE-2026-23217, CVE-2026-23218, CVE-2026-23219, CVE-2026-23223, CVE-2026-23224, CVE-2026-23225, CVE-2026-23232, CVE-2026-23241, CVE-2026-23248, CVE-2026-23249, CVE-2026-23250, CVE-2026-23251, CVE-2026-23252, CVE-2026-23259, CVE-2026-23263, CVE-2026-23275, CVE-2026-23280, CVE-2026-23282, CVE-2026-23283, CVE-2026-23288, CVE-2026-23294, CVE-2026-23295, CVE-2026-23297, CVE-2026-23299, CVE-2026-23301, CVE-2026-23305, CVE-2026-23311, CVE-2026-23314, CVE-2026-23316, CVE-2026-23322, CVE-2026-23323, CVE-2026-23326, CVE-2026-23328, CVE-2026-23329, CVE-2026-23331, CVE-2026-23332, CVE-2026-23337, CVE-2026-23338, CVE-2026-23341, CVE-2026-23342, CVE-2026-23344, CVE-2026-23345, CVE-2026-23349, CVE-2026-23350, CVE-2026-23353, CVE-2026-23354, CVE-2026-23355, CVE-2026-23358, CVE-2026-23363, CVE-2026-23366, CVE-2026-23369, CVE-2026-23373, CVE-2026-23375, CVE-2026-23376, CVE-2026-23380, CVE-2026-23384, CVE-2026-23385, CVE-2026-23390, CVE-2026-23394, CVE-2026-23400, CVE-2026-23402, CVE-2026-23415, CVE-2026-23416 and CVE-2026-23417

- ncurses: Fix CVE-2025-69720
- nghttp2: Fix CVE-2026-27135
- ovmf: Fix CVE-2024-38798 and CVE-2025-2296
- python3-pyasn1: Fix CVE-2026-23490
- python3-wheel: Fix CVE-2026-24049
- rsync: Fix CVE-2026-41035
- sqlite3: Fix CVE-2025-70873



- sudo: Fix CVE-2026-35535
- systemd: Fix CVE-2026-40225 and CVE-2026-40226
- u-boot: Fix CVE-2025-24857
- vim: Fix CVE-2026-25749, CVE-2026-26269, CVE-2026-28418, CVE-2026-28419, CVE-2026-33412 and CVE-2026-39881

### Fixes in Yocto-5.0.18

- apt: Add *CVE\_PRODUCT* to support product name
- apt: Fix build with GCC 15
- archiver: Don't try to preserve all attributes when copying files
- base-passwd: upgrade 3.6.8
- binutils: backport patch to fix build with glibc-2.43 on host
- bitbake: fetch/git: Fix leaking of temporary directory
- bitbake: fetch2/crate: use CDN for fetching crates
- bitbake: runqueue.py: make sure we use bb multiprocessing
- bitbake: tests/fetch: Avoid using git protocol in tests
- build-appliance-image: switch *SRC\_URI* to https protocol
- build-appliance-image: Update to scarthgap head revisions
- ca-certificates: upgrade to 20260223
- cmake: backport a fix for gcc-16 on host
- contributor-guide/submit-changes.rst: Added missing word
- coreutils: set *CVE\_PRODUCT*
- db: Pin to use C99 std
- dbus: gate user-session *PACKAGECONFIG* on systemd in *DISTRO\_FEATURES*
- dbus: use \${PN} in pkg\_postinst instead of 'dbus'
- dev-manual: "--runonly" should be "--runall"
- devtool: Disable gpg signing when setting up source tree repos
- dtc: backport fix for build with glibc-2.43
- elfutils: don't add -Werror to avoid discarded-qualifiers
- gcc: backport a fix for building with gcc-16
- ghostscript: fix build with gcc-15 on host
- ghostscript: Pin to C17 std
- glibc: Fix recipe bug that disabled stack protector

- grub: update search parameter
- kernel-devsrc: make tools/Build optional
- lib/oeqa/utis/httpserver: use multiprocessing from bb
- libatomic-ops: upgrade to 7.8.4
- liburcu: upgrade to 0.14.2
- libxcrypt: avoid discarded-qualifiers build failure with glibc 2.43
- libxcrypt: Fix build wrt C23 support
- libxcrypt: Use configure knob to disable warnings as errors
- license.py: Drop visit\_Str from SeenVisitor in selftest
- linux-yocto/6.6: update to v6.6.127
- linux/generate-cve-exclusions: backport script from master branch
- ltp: fix epoll\_ctl04 failed
- ltng-ust: upgrade to 2.13.10
- mesa: fix build on host with glibc-2.43
- meta/files/layers.example.json: switch to https clone URIs
- migration-guide: add release notes for 4.0.33 4.0.34 5.0.17
- oeqa/sdk: Default to https git protocol for YP/OE repos
- oeqa/selftest/git-submodule-test: Default to https git protocol for YP/OE repos
- openssl: upgrade to 3.5.6
- overview-manual/concepts.rst: fix do\_prepare\_recipe\_sysroot task description
- ovmf: backport a fix for build with gcc-16
- poky.conf: Bump version for 5.0.18 release
- poky: Fix CentOS Stream distro names
- pseudo: Add fix for glibc 2.43
- python3: upgrade to 3.12.13
- qemu: backport patches to support python 3.14
- ref-manual/variables.rst: update COMPONENTS\_DIR's PKGDATA\_DIR's RECIPE\_SYSROOT\* STAGING\_DIR\* descriptions
- scripts: Default to https git protocol for YP/OE repos
- selftest/gdbserver: replace shutil.unpack\_archive with tarfile extract
- selftest/minidebuginfo: extract files from tar archive using tarfile module
- selftest/scripts: Update old git protocol references
- spdx30\_tasks: fix condition in create\_spdx

- sphinx-static/theme\_overrides.css: switch to a fixed width documentation
- spirv-tools: backport a fix for building with gcc-16
- sudo: upgrade to 1.9.17p2
- tcl: skip http11 tests
- texinfo: Backport patches for hosts with newer GCC
- tzdata/tzcode-native: upgrade to 2026a
- unfs3: Fix race issue causing a glibc test hang
- variables.rst: expand explanation of *RSUGGESTS*
- virglrenderer: Fix build with glibc 2.43+
- yocto-uninative: Update to 5.1 for glibc 2.43

### Known Issues in Yocto-5.0.18

- N/A

### Contributors to Yocto-5.0.18

Thanks to the following people who contributed to this release:

- Adam Blank
- Adarsh Jagadish Kamini
- Alexander Kanavin
- Andrej Kozemcak
- Anil Dongare
- Antonin Godard
- Bruce Ashfield
- Changqing Li
- Daniel Turull
- Dawid Bijak
- Fabien Thomas
- Guocai He
- Hemanth Kumar M D
- Himanshu Jadon
- Hitendra Prajapati
- Hongxu Jia
- Hugo SIMELIERE
- Ivan Nestlerode

- Jhonata Poma-Hansen
- Jiaying Song
- Jinfeng Wang
- Johan Anderholm
- João Marcos Costa (Schneider Electric)
- Khem Raj
- Lee Chee Yang
- Li Wang
- Martin Jansa
- Michael Halstead
- Mingli Yu
- Moritz Haase
- Paul Barker
- Peter Marko
- Richard Purdie
- Robert P. J. Day
- Ross Burton
- Sudhir Dumbhare
- Sunil Dora
- Trevor Gamblin
- Vijay Anusuri
- Xiangyu Chen
- Yanis BINARD
- Yoann Congal
- Zhang Peng

## **Repositories / Downloads for Yocto-5.0.18**

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.18](#)
- Git Revision: [1c5e7f136d7460fa5ad4c8a49ab1de31bd670e59](#)
- Release Artefact: [yocto-docs-1c5e7f136d7460fa5ad4c8a49ab1de31bd670e59](#)

- sha: 2787473919e2f72b3c35615b5406724f1f3e44f4573cad378fd3842f84a4ad16

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.18/yocto-docs-1c5e7f136d7460fa5ad4c8a49ab1de31bd670e59.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.18/yocto-docs-1c5e7f136d7460fa5ad4c8a49ab1de31bd670e59.tar.bz2>

#### poky

- Repository Location: <https://git.yoctoproject.org/poky>

- Branch: scarthgap

- Tag: yocto-5.0.18

- Git Revision: 44dcf08572ce391d7c0df4f8c7510af5e096baca

- Release Artefact: poky-44dcf08572ce391d7c0df4f8c7510af5e096baca

- sha: dd1868e72511b07ae02744ac9f90b278fc06baeb2175f7ed31b2de1cd2531a98

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.18/poky-44dcf08572ce391d7c0df4f8c7510af5e096baca.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.18/poky-44dcf08572ce391d7c0df4f8c7510af5e096baca.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>

- Branch: scarthgap

- Tag: yocto-5.0.18

- Git Revision: ece80784b493c8b7493478fa2ba0dc1d6d80aa79

- Release Artefact: oecore-ece80784b493c8b7493478fa2ba0dc1d6d80aa79

- sha: 243fe6badad99538c88bea72338df13c8682868bb126c05819b837988b89aefa

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.18/oecore-ece80784b493c8b7493478fa2ba0dc1d6d80aa79.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.18/oecore-ece80784b493c8b7493478fa2ba0dc1d6d80aa79.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>

- Branch: scarthgap

- Tag: yocto-5.0.18

- Git Revision: [ca5a51aadaf651881d640688dc3e1e123aa30bf6](#)
- Release Artefact: [meta-yocto-ca5a51aadaf651881d640688dc3e1e123aa30bf6](#)
- sha: [30d5bc789b0c28a84b6333d7e81e204aac27d9ce7ffc265281952cba031dbe00](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.18/meta-yocto-ca5a51aadaf651881d640688dc3e1e123aa30bf6.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.18/meta-yocto-ca5a51aadaf651881d640688dc3e1e123aa30bf6.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.18](#)
- Git Revision: [bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f](#)
- Release Artefact: [meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f](#)
- sha: [ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.18/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.18/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.8](#)
- Tag: [yocto-5.0.18](#)
- Git Revision: [82abbfcdbda949851a03bb2cb2049ea689564ad6](#)
- Release Artefact: [bitbake-82abbfcdbda949851a03bb2cb2049ea689564ad6](#)
- sha: [e20ae44c0f4b0e921b23985f2b599a55a7d0cc114cbf709400e5c740691c4f56](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.18/bitbake-82abbfcdbda949851a03bb2cb2049ea689564ad6.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.18/bitbake-82abbfcdbda949851a03bb2cb2049ea689564ad6.tar.bz2>

## 17.7.21 Release notes for Yocto-5.0.19 (Scarthgap)

gawk-native is now built from source instead of used from the host when building grub2 & glibc to avoid reproducibility issues on newer host distros.

### Security Fixes in Yocto-5.0.19

- avahi: Remove a reference to the rejected CVE-2021-36217
- binutils: Fix CVE-2025-69644
- busybox: Fix CVE-2026-29004
- dpkg: Fix CVE-2026-2219
- go: Fix CVE-2025-58183, CVE-2026-25679, CVE-2026-27140, CVE-2026-27142, CVE-2026-27143, CVE-2026-27144, CVE-2026-27145, CVE-2026-32280, CVE-2026-32283, CVE-2026-32288, CVE-2026-32289, CVE-2026-33811, CVE-2026-39817, CVE-2026-39819, CVE-2026-39820, CVE-2026-39825, CVE-2026-39826, CVE-2026-42499, CVE-2026-42501, CVE-2026-42504 and CVE-2026-42507
- go: Ignore CVE-2026-39836
- libarchive: Fix CVE-2026-4424
- libexif: Fix CVE-2026-32775, CVE-2026-40385 and CVE-2026-40386
- libinput: Fix CVE-2026-50292
- libpng: Fix CVE-2026-33416
- libsolv: Fix CVE-2026-9150
- libsoup: Fix CVE-2025-11021 and CVE-2026-2369
- libssh2: Fix CVE-2026-7598
- libusb1: Fix CVE-2026-23679 and CVE-2026-47104
- libxml-parser-perl: Fix CVE-2006-10003
- linux-yocto/6.6: Fix CVE-2023-52920, CVE-2024-14027, CVE-2024-27022, CVE-2024-56647, CVE-2025-21739, CVE-2025-22125, CVE-2025-38531, CVE-2025-38584, CVE-2025-38710, CVE-2025-39981, CVE-2025-40219, CVE-2025-68315, CVE-2025-71184, CVE-2025-71239, CVE-2025-71265, CVE-2025-71266, CVE-2025-71267, CVE-2025-71269, CVE-2025-71274, CVE-2025-71286, CVE-2025-71287, CVE-2025-71288, CVE-2025-71291, CVE-2025-71292, CVE-2025-71295, CVE-2025-71297, CVE-2025-71304, CVE-2025-71305, CVE-2026-23004, CVE-2026-23171, CVE-2026-23231, CVE-2026-23242, CVE-2026-23243, CVE-2026-23244, CVE-2026-23245, CVE-2026-23246, CVE-2026-23253, CVE-2026-23255, CVE-2026-23268, CVE-2026-23269, CVE-2026-23270, CVE-2026-23271, CVE-2026-23272, CVE-2026-23273, CVE-2026-23274, CVE-2026-23277, CVE-2026-23279, CVE-2026-23281, CVE-2026-23284, CVE-2026-23285, CVE-2026-23286, CVE-2026-23287, CVE-2026-23289, CVE-2026-23290, CVE-2026-23291, CVE-2026-23292, CVE-2026-23293, CVE-2026-23296, CVE-2026-23298, CVE-2026-23300, CVE-2026-23302, CVE-2026-23303, CVE-2026-23304, CVE-2026-23306, CVE-2026-23307, CVE-2026-23308, CVE-2026-23310, CVE-2026-23312, CVE-2026-23313, CVE-2026-23315, CVE-2026-23317, CVE-2026-23318, CVE-2026-23319, CVE-2026-23321, CVE-2026-23324, CVE-2026-23325, CVE-2026-23330, CVE-2026-23334, CVE-2026-23335, CVE-2026-23336, CVE-2026-23339,

[illegible]



17.7. Release 5.0 (scarthgap) 1465



46089, CVE-2026-46091, CVE-2026-46094, CVE-2026-46098, CVE-2026-46099, CVE-2026-46101, CVE-2026-46102, CVE-2026-46103, CVE-2026-46106, CVE-2026-46107, CVE-2026-46108, CVE-2026-46110, CVE-2026-46111, CVE-2026-46112, CVE-2026-46113, CVE-2026-46114, CVE-2026-46115, CVE-2026-46116, CVE-2026-46119, CVE-2026-46120, CVE-2026-46121, CVE-2026-46122, CVE-2026-46123, CVE-2026-46124, CVE-2026-46125, CVE-2026-46127, CVE-2026-46128, CVE-2026-46129, CVE-2026-46131, CVE-2026-46132, CVE-2026-46133, CVE-2026-46136, CVE-2026-46137, CVE-2026-46138, CVE-2026-46142, CVE-2026-46143, CVE-2026-46144, CVE-2026-46145, CVE-2026-46146, CVE-2026-46149, CVE-2026-46150, CVE-2026-46151, CVE-2026-46152, CVE-2026-46155, CVE-2026-46158, CVE-2026-46159, CVE-2026-46160, CVE-2026-46161, CVE-2026-46163, CVE-2026-46164, CVE-2026-46167, CVE-2026-46168, CVE-2026-46169, CVE-2026-46170, CVE-2026-46172, CVE-2026-46173, CVE-2026-46174, CVE-2026-46176, CVE-2026-46177, CVE-2026-46178, CVE-2026-46179, CVE-2026-46180, CVE-2026-46184, CVE-2026-46185, CVE-2026-46186, CVE-2026-46187, CVE-2026-46189, CVE-2026-46190, CVE-2026-46191, CVE-2026-46193, CVE-2026-46194, CVE-2026-46195, CVE-2026-46196, CVE-2026-46197, CVE-2026-46198, CVE-2026-46199, CVE-2026-46204, CVE-2026-46205, CVE-2026-46206, CVE-2026-46208, CVE-2026-46209, CVE-2026-46212, CVE-2026-46214, CVE-2026-46218, CVE-2026-46219, CVE-2026-46220, CVE-2026-46225, CVE-2026-46226, CVE-2026-46227, CVE-2026-46229, CVE-2026-46230, CVE-2026-46231, CVE-2026-46232, CVE-2026-46233, CVE-2026-46234, CVE-2026-46235, CVE-2026-46236, CVE-2026-46238, CVE-2026-46243, CVE-2026-46244, CVE-2026-46247, CVE-2026-46249, CVE-2026-46250, CVE-2026-46251, CVE-2026-46253, CVE-2026-46255, CVE-2026-46259, CVE-2026-46260, CVE-2026-46261, CVE-2026-46262, CVE-2026-46265, CVE-2026-46266, CVE-2026-46267, CVE-2026-46270, CVE-2026-46273, CVE-2026-46274, CVE-2026-46275, CVE-2026-46276, CVE-2026-46280, CVE-2026-46285, CVE-2026-46286, CVE-2026-46287, CVE-2026-46289, CVE-2026-46291, CVE-2026-46292, CVE-2026-46293, CVE-2026-46294, CVE-2026-46296, CVE-2026-46299, CVE-2026-46300, CVE-2026-46301, CVE-2026-46303, CVE-2026-46304, CVE-2026-46306, CVE-2026-46307, CVE-2026-46312, CVE-2026-46319, CVE-2026-46323, CVE-2026-46328, CVE-2026-46333, CVE-2026-52911, CVE-2026-52912, CVE-2026-52914, CVE-2026-52915, CVE-2026-52916, CVE-2026-52918, CVE-2026-52919, CVE-2026-52920, CVE-2026-52921, CVE-2026-52922, CVE-2026-52923, CVE-2026-52925, CVE-2026-52926, CVE-2026-52931, CVE-2026-52933, CVE-2026-52936, CVE-2026-52941, CVE-2026-53128, CVE-2026-53130, CVE-2026-53279, CVE-2026-53287, CVE-2026-53289, CVE-2026-53291, CVE-2026-53293, CVE-2026-53294, CVE-2026-53295, CVE-2026-53296, CVE-2026-53303, CVE-2026-53304, CVE-2026-53306, CVE-2026-53309, CVE-2026-53314 and CVE-2026-53320

- linux-yocto/6.6: Ignore CVE-2023-53012, CVE-2023-53187, CVE-2024-26949, CVE-2024-26997, CVE-2024-35983, CVE-2024-36002, CVE-2024-36288, CVE-2024-38542, CVE-2024-38595, CVE-2024-40920, CVE-2024-40921, CVE-2024-40986, CVE-2024-42111, CVE-2024-42112, CVE-2024-42150, CVE-2024-43820, CVE-2024-43838, CVE-2024-47711, CVE-2024-49854, CVE-2024-50042, CVE-2024-50097, CVE-2024-50203, CVE-2024-50206, CVE-2024-50238, CVE-2024-50241, CVE-2024-50249, CVE-2024-50281, CVE-2024-53073, CVE-2024-53097, CVE-2024-53115, CVE-2024-53133, CVE-2024-53169, CVE-2024-53201, CVE-2024-54191, CVE-2024-54460, CVE-2024-56542, CVE-2024-56550, CVE-2024-56561, CVE-2024-56782, CVE-2024-57805, CVE-2024-57852, CVE-2024-57879, CVE-2024-57935, CVE-2024-57952, CVE-2024-57990, CVE-2024-58008, CVE-2024-58081, CVE-2025-21752, CVE-2025-21809, CVE-2025-21813, CVE-2025-21902, CVE-2025-22026, CVE-2025-22030, CVE-2025-22032, CVE-2025-22069, CVE-2025-22112, CVE-2025-37760, CVE-2025-37814, CVE-2025-37827, CVE-2025-37845, CVE-2025-37868, CVE-2025-37871, CVE-2025-37878, CVE-2025-37895,

CVE-2025-37929, CVE-2025-37962, CVE-2025-37974, CVE-2025-38055, CVE-2025-38098, CVE-2025-38099, CVE-2025-38162, CVE-2025-38169, CVE-2025-38201, CVE-2025-38224, CVE-2025-38234, CVE-2025-38289, CVE-2025-38325, CVE-2025-38372, CVE-2025-38373, CVE-2025-38405, CVE-2025-38421, CVE-2025-38484, CVE-2025-38551, CVE-2025-38567, CVE-2025-38675, CVE-2025-38733, CVE-2025-38736, CVE-2025-39688, CVE-2025-39725, CVE-2025-39775, CVE-2025-39807, CVE-2025-39872, CVE-2025-39930, CVE-2025-39948, CVE-2025-39965, CVE-2025-39999, CVE-2025-40005, CVE-2025-40007, CVE-2025-40082, CVE-2025-40101, CVE-2025-40131, CVE-2025-40199, CVE-2025-40213, CVE-2025-40290, CVE-2025-40327, CVE-2025-40332, CVE-2025-40344, CVE-2025-68195, CVE-2025-68207, CVE-2025-68213, CVE-2025-68215, CVE-2025-68298, CVE-2025-68351, CVE-2025-68357, CVE-2025-68358, CVE-2025-68823, CVE-2025-71070, CVE-2025-71076, CVE-2025-71135, CVE-2025-71145, CVE-2025-71146, CVE-2025-71155, CVE-2025-71204, CVE-2025-71220, CVE-2025-71222, CVE-2025-71223, CVE-2025-71224, CVE-2025-71229, CVE-2025-71232, CVE-2025-71233, CVE-2025-71235, CVE-2025-71236, CVE-2025-71237, CVE-2025-71238, CVE-2025-71268, CVE-2025-71270, CVE-2025-71271, CVE-2025-71290, CVE-2025-71293, CVE-2025-71294, CVE-2025-71296, CVE-2025-71298, CVE-2025-71299, CVE-2025-71300, CVE-2025-71301, CVE-2025-71302, CVE-2026-23014, CVE-2026-23018, CVE-2026-23079, CVE-2026-23100, CVE-2026-23111, CVE-2026-23112, CVE-2026-23143, CVE-2026-23148, CVE-2026-23151, CVE-2026-23166, CVE-2026-23169, CVE-2026-23176, CVE-2026-23178, CVE-2026-23180, CVE-2026-23182, CVE-2026-23187, CVE-2026-23189, CVE-2026-23190, CVE-2026-23193, CVE-2026-23198, CVE-2026-23200, CVE-2026-23201, CVE-2026-23202, CVE-2026-23204, CVE-2026-23205, CVE-2026-23206, CVE-2026-23209, CVE-2026-23216, CVE-2026-23217, CVE-2026-23220, CVE-2026-23221, CVE-2026-23222, CVE-2026-23228, CVE-2026-23229, CVE-2026-23230, CVE-2026-23233, CVE-2026-23234, CVE-2026-23235, CVE-2026-23236, CVE-2026-23237, CVE-2026-23238, CVE-2026-23254, CVE-2026-23256, CVE-2026-23257, CVE-2026-23258, CVE-2026-23260, CVE-2026-23261, CVE-2026-23262, CVE-2026-23264, CVE-2026-23266, CVE-2026-23267, CVE-2026-23288, CVE-2026-23341, CVE-2026-23355, CVE-2026-23376, CVE-2026-23418, CVE-2026-23421, CVE-2026-23423, CVE-2026-23424, CVE-2026-23425, CVE-2026-23429, CVE-2026-23430, CVE-2026-23431, CVE-2026-23432, CVE-2026-23433, CVE-2026-23435, CVE-2026-23436, CVE-2026-23437, CVE-2026-23445, CVE-2026-23451, CVE-2026-23453, CVE-2026-23459, CVE-2026-23464, CVE-2026-23466, CVE-2026-23467, CVE-2026-23469, CVE-2026-23470, CVE-2026-31390, CVE-2026-31394, CVE-2026-31395, CVE-2026-31397, CVE-2026-31398, CVE-2026-31401, CVE-2026-31404, CVE-2026-31406, CVE-2026-31413, CVE-2026-31435, CVE-2026-31436, CVE-2026-31437, CVE-2026-31438, CVE-2026-31442, CVE-2026-31443, CVE-2026-31444, CVE-2026-31445, CVE-2026-31456, CVE-2026-31457, CVE-2026-31459, CVE-2026-31460, CVE-2026-31461, CVE-2026-31463, CVE-2026-31465, CVE-2026-31468, CVE-2026-31470, CVE-2026-31471, CVE-2026-31472, CVE-2026-31475, CVE-2026-31479, CVE-2026-31481, CVE-2026-31484, CVE-2026-31490, CVE-2026-31491, CVE-2026-31499, CVE-2026-31501, CVE-2026-31511, CVE-2026-31513, CVE-2026-31514, CVE-2026-31517, CVE-2026-31526, CVE-2026-31529, CVE-2026-31535, CVE-2026-31538, CVE-2026-31539, CVE-2026-31541, CVE-2026-31543, CVE-2026-31544, CVE-2026-31547, CVE-2026-31553, CVE-2026-31554, CVE-2026-31556, CVE-2026-31558, CVE-2026-31559, CVE-2026-31561, CVE-2026-31562, CVE-2026-31564, CVE-2026-31567, CVE-2026-31569, CVE-2026-31571, CVE-2026-31572, CVE-2026-31573, CVE-2026-31574, CVE-2026-31575, CVE-2026-31582, CVE-2026-31589, CVE-2026-31591, CVE-2026-31593, CVE-2026-31600, CVE-2026-31601, CVE-2026-31608, CVE-2026-31609, CVE-2026-31620, CVE-2026-31621, CVE-2026-31631, CVE-2026-31632, CVE-2026-31633, CVE-2026-31635, CVE-2026-31636, CVE-2026-31640, CVE-2026-31641, CVE-2026-31643, CVE-2026-31644, CVE-2026-31647, CVE-2026-31650, CVE-2026-31652, CVE-2026-31653, CVE-2026-31654, CVE-2026-

31666, CVE-2026-31687, CVE-2026-31690, CVE-2026-31691, CVE-2026-31703, CVE-2026-31710, CVE-2026-31713, CVE-2026-31719, CVE-2026-31727, CVE-2026-31731, CVE-2026-31732, CVE-2026-31733, CVE-2026-31734, CVE-2026-31735, CVE-2026-31736, CVE-2026-31739, CVE-2026-31742, CVE-2026-31743, CVE-2026-31744, CVE-2026-31745, CVE-2026-31746, CVE-2026-31750, CVE-2026-31753, CVE-2026-31757, CVE-2026-31760, CVE-2026-31764, CVE-2026-31765, CVE-2026-31766, CVE-2026-31769, CVE-2026-31772, CVE-2026-31774, CVE-2026-31775, CVE-2026-31776, CVE-2026-31782, CVE-2026-31783, CVE-2026-31784, CVE-2026-31785, CVE-2026-43004, CVE-2026-43005, CVE-2026-43006, CVE-2026-43008, CVE-2026-43012, CVE-2026-43021, CVE-2026-43031, CVE-2026-43034, CVE-2026-43039, CVE-2026-43045, CVE-2026-43055, CVE-2026-43059, CVE-2026-43063, CVE-2026-43070, CVE-2026-43084, CVE-2026-43087, CVE-2026-43090, CVE-2026-43095, CVE-2026-43096, CVE-2026-43097, CVE-2026-43100, CVE-2026-43102, CVE-2026-43106, CVE-2026-43108, CVE-2026-43121, CVE-2026-43122, CVE-2026-43131, CVE-2026-43138, CVE-2026-43142, CVE-2026-43144, CVE-2026-43146, CVE-2026-43151, CVE-2026-43154, CVE-2026-43155, CVE-2026-43160, CVE-2026-43164, CVE-2026-43165, CVE-2026-43166, CVE-2026-43169, CVE-2026-43174, CVE-2026-43175, CVE-2026-43176, CVE-2026-43177, CVE-2026-43178, CVE-2026-43179, CVE-2026-43181, CVE-2026-43188, CVE-2026-43191, CVE-2026-43192, CVE-2026-43193, CVE-2026-43195, CVE-2026-43201, CVE-2026-43208, CVE-2026-43210, CVE-2026-43217, CVE-2026-43220, CVE-2026-43224, CVE-2026-43228, CVE-2026-43229, CVE-2026-43235, CVE-2026-43237, CVE-2026-43243, CVE-2026-43247, CVE-2026-43254, CVE-2026-43259, CVE-2026-43260, CVE-2026-43263, CVE-2026-43267, CVE-2026-43272, CVE-2026-43274, CVE-2026-43276, CVE-2026-43280, CVE-2026-43282, CVE-2026-43285, CVE-2026-43286, CVE-2026-43290, CVE-2026-43292, CVE-2026-43293, CVE-2026-43297, CVE-2026-43300, CVE-2026-43301, CVE-2026-43305, CVE-2026-43306, CVE-2026-43307, CVE-2026-43320, CVE-2026-43321, CVE-2026-43322, CVE-2026-43323, CVE-2026-43325, CVE-2026-43326, CVE-2026-43335, CVE-2026-43337, CVE-2026-43346, CVE-2026-43347, CVE-2026-43348, CVE-2026-43349, CVE-2026-43351, CVE-2026-43354, CVE-2026-43356, CVE-2026-43358, CVE-2026-43364, CVE-2026-43367, CVE-2026-43369, CVE-2026-43374, CVE-2026-43375, CVE-2026-43384, CVE-2026-43385, CVE-2026-43388, CVE-2026-43389, CVE-2026-43390, CVE-2026-43391, CVE-2026-43392, CVE-2026-43393, CVE-2026-43394, CVE-2026-43395, CVE-2026-43396, CVE-2026-43398, CVE-2026-43399, CVE-2026-43400, CVE-2026-43401, CVE-2026-43402, CVE-2026-43403, CVE-2026-43404, CVE-2026-43408, CVE-2026-43410, CVE-2026-43417, CVE-2026-43418, CVE-2026-43422, CVE-2026-43423, CVE-2026-43431, CVE-2026-43433, CVE-2026-43434, CVE-2026-43435, CVE-2026-43438, CVE-2026-43440, CVE-2026-43442, CVE-2026-43444, CVE-2026-43446, CVE-2026-43447, CVE-2026-43454, CVE-2026-43460, CVE-2026-43461, CVE-2026-43462, CVE-2026-43463, CVE-2026-43467, CVE-2026-43470, CVE-2026-43474, CVE-2026-43477, CVE-2026-43478, CVE-2026-43479, CVE-2026-43481, CVE-2026-43482, CVE-2026-43485, CVE-2026-43486, CVE-2026-43487, CVE-2026-43489 and CVE-2026-43498

- lz4: Remove a reference to the rejected CVE-2025-62813
- nfs-utils: Fix CVE-2025-12801
- openssh: Fix CVE-2026-35386, CVE-2026-35385, CVE-2026-35387 and CVE-2026-35388
- python3-requests: Fix CVE-2026-25645
- python3: Fix CVE-2025-13462, CVE-2026-0672, CVE-2026-1502, CVE-2026-3644, CVE-2026-4224, CVE-2026-4519, CVE-2026-4786, CVE-2026-6019 and CVE-2026-6100

- python3: Ignore [CVE-2026-3087](#)
- qemu: Fix [CVE-2024-6519](#)
- qemu: fix [CVE-2025-11234](#)
- rust,libstd-rs: Ignore [CVE-2024-3566](#)
- tiff: fix [CVE-2026-4775](#)
- util-linux: Fix [CVE-2026-27456](#)
- xserver-xorg: Fix [CVE-2026-33999](#), [CVE-2026-34000](#), [CVE-2026-34001](#), [CVE-2026-34002](#) and [CVE-2026-34003](#)
- xwayland: Fix [CVE-2026-33999](#), [CVE-2026-34000](#), [CVE-2026-34001](#), [CVE-2026-34002](#) and [CVE-2026-34003](#)
- xz: Fix [CVE-2026-34743](#)

### Fixes in Yocto-5.0.19

- apr-util: Add [CVE\\_PRODUCT](#) to support product name
- apr: Add [CVE\\_PRODUCT](#) to support product name
- bitbake: data: fix issue with varflag exclusion
- bitbake: fetch2/git: quote shallow extra ref arguments
- bitbake: fetch2/wget: handle HTTP 308 Permanent Redirect
- bitbake: fetch2/wget: limit auth on checkstatus redirects
- bitbake: fetch2: Unpack RPMs with --no-absolute-filenames
- bitbake: fetch2: validate deb/ipk data member names
- bitbake: fetch2: validate striplevel parameter
- bitbake: hashserv/tests: use valid 64-character unihashes
- bitbake: hashserv: validate unihash values
- bitbake: tests/fetch: cover checkstatus redirect auth handling
- bsp-guide: mention bootloader and device tree in BSP intro
- bsp-guide: update guide to reflect newer beaglebone
- build-appliance-image: Update to scarthgap head revisions
- build-manual: update [ROOTFS\\_POSTPROCESS\\_COMMAND](#) example
- bzip2: set [CVE\\_PRODUCT](#)
- cargo: set [CVE\\_PRODUCT](#)
- classes/base: prefer gnu-prefixed [HOSTTOOLS](#)
- classes/gtk-icon-cache: fix libdir passed to the postrm intercept
- conf/machine: fix typos in ARM and x86 README files

- contributor-guide: couple minor typo/grammar fixes
- contributor-guide: fix type "maintainance" to "maintenance"
- dev-manual: drop "PREFERRED\_VERSION" from x86-base.inc snippet
- dev-manual: fix broken grammar in "Libraries" section
- dev-manual: fix grammatical error, missing word "with"
- dev-manual: fully define SOLIBS-related variables in bitbake.conf
- dev-manual: remove semicolons for rootfs commands
- dev-manual: SysVinit is the default init manager for Poky
- dev-manual: update *AUTOREV* explanation to match current file
- devtool: prevent 'devtool modify -n' from corrupting kernel Git repos
- docs: conf.py: add a :yocto\_bug: role
- docs: conf.py: define new \*\_path roles
- docs: conf.py: define new {oecore,bitbake,meta\_yocto}\_rev roles
- docs: index.rst: update "Software Overview" to "Technical Overview"
- docs: "Transitioning ..." Various pedantic cleanups
- docs: What I Wish I'd Known: Various pedantic cleanups
- docs: YP Quick Build: delete extraneous periods in list
- gawk-native: fix gcc-15/C23 compilation issues
- gawk: trim native build configuration
- gawk: use native gawk when building glibc and grub
- gdb: backport a patch to fix static\_assert in recent GCC
- gnupg: upgrade to 2.4.9
- go.bbclass: change GOTMPDIR to improve reproducibility
- go.bbclass: disable workspaces
- grub/glibc: Bump versions to resolve hashequiv/reproducibility issues
- kernel-dev: remove references to defunct LTSI project
- linux-yocto/6.6: address ltp hang
- linux-yocto/6.6: genericarm64 fix configuration audit warning
- linux-yocto/6.6: update to v6.6.142
- ltng-modules: Fix trace\_hrtimer\_start build failure
- meta/lib/oe/package.py: fix path to kernel sources in save\_debugsources\_info
- meta: fix generation of kernel CONFIGi\_ in SPDX3



- migration-guide: add release notes for 4.0.35 5.0.18
- oeqa/core/runner: stub addDuration in OETestResult
- oeqa/runtime/parselogs: update pci BAR ignore for kernel 6.10
- oeqa: Drop /git/ from our urls
- oeqa: runtime: go: Increase test\_go\_compile/test\_go\_module timeout
- openssl: upgrade to 3.5.7
- overview-manual: add ":term:" for OE Build System
- overview-manual: fix "checkout" versus "check out"
- overview-manual: fix typo, "semi-colon" -> "colon"
- overview-manual: hyphens not allowed in file version
- overview-manual: inform the reader early of "bitbake-getvar"
- overview-manual: mention that patch files can be compressed
- overview-manual: provide a more expansive definition of "layer"
- overview-manual: remind reader that meta-poky is a distro layer
- overview-manual: update deploy.bbclass snippet
- overview-manual: use correct spelling "counterpart"
- overview-manual: yp-intro.rst: add link to "buildbot"
- overview-manual: yp-intro.rst: delete really old references
- perl: link to the system zlib instead of a vendored copy
- poky.conf: Bump version for 5.0.19 release
- pseudo: Update to 1.9.8
- python\_setuptools\_build\_meta: clean the build directory in configure
- recipe-style-guide.rst: two minor grammatical tweaks
- recipetool: Recognise <https://git>. as git urls
- ref-manual/variables.rst: link \*MIRRORS definitions to the BitBake manual
- ref-manual: add more explanation to glossary variable *LICENSE*
- ref-manual: clarify that *PACKAGE\_EXCLUDE* supports DEB packaging
- ref-manual: clarify use of "PACKAGE\_ARCH" in a packagegroup
- ref-manual: document *RM\_WORK\_EXCLUDE\_ITEMS* variable
- scripts/install-buildtools: Update to 5.0.18
- security-team.rst: update my email address and key
- security-team: Add section on multi-project embargoes



- security-team: Tidy and update section on security team operations
- security-team: Update membership list
- setuptools3: clean the build directory in configure
- setuptools3\_legacy: ensure \${B} is clean
- systemd: update musl specific patch to apply
- tzdata/tzcode-native: upgrade to 2026b
- wic: filemap: use separate fd for SEEK\_HOLE probes

### Known Issues in Yocto-5.0.19

- N/A

### Contributors to Yocto-5.0.19

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Alexander Kanavin
- Amaury Couderc
- Anders Heimer
- Anil Dongare
- Ankur Tyagi
- Antonin Godard
- Benjamin Robin (Schneider Electric)
- Bruce Ashfield
- Changqing Li
- Deepak Rathore
- Enrico Jörns
- Guðni Már Gilbert
- He Zhe
- Himanshu Jadon
- Hitendra Prajapati
- Hugo SIMELIERE (Schneider Electric)
- Jonas Munsin
- João Marcos Costa (Schneider Electric)
- Lee Chee Yang
- Marcio Henriques

- Mark Hatle
- Marta Rybczynska
- Martin Jansa
- Mathieu Dubois-Briand
- Naman Jain
- Paul Barker
- Peter Bergin
- Peter Marko
- Prabhudasu Vatala
- Richard Purdie
- Robert P. J. Day
- Ross Burton
- Shubham Pushpkar
- Sudhir Dumbhare
- Theo Gage (Schneider Electric)
- Trevor Woerner
- Vijay Anusuri
- Yoann Congal
- Zahir Hussain

## Repositories / Downloads for Yocto-5.0.19

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.19](#)
- Git Revision: [1b819d324780a699d9307a2d4e68c69b576ab748](#)
- Release Artefact: [yocto-docs-1b819d324780a699d9307a2d4e68c69b576ab748](#)
- sha: [b2c484d8d13b05b133f6f23f44e7757e4b53d93c27c9ea76d1a2e5f759f51af0](#)
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.19/yocto-docs-1b819d324780a699d9307a2d4e68c69b576ab748.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.19/yocto-docs-1b819d324780a699d9307a2d4e68c69b576ab748.tar.bz2>

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `scarthgap`
- Tag: `yocto-5.0.19`
- Git Revision: `bb98354685781296e3b3737e7762412100f359c2`
- Release Artefact: `poky-bb98354685781296e3b3737e7762412100f359c2`
- sha: `37fd9eeff8043e6d7d595421b8ac40d38357d2d4ce3a6d0f86a0f7d884c995c3`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.19/poky-bb98354685781296e3b3737e7762412100f359c2.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.19/poky-bb98354685781296e3b3737e7762412100f359c2.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `scarthgap`
- Tag: `yocto-5.0.19`
- Git Revision: `2814f0962f56c8d1afa4de76d2895ba9b5cb767d`
- Release Artefact: `oecore-2814f0962f56c8d1afa4de76d2895ba9b5cb767d`
- sha: `8556e454499fcda4026dc58fb8fc627861720f5c006bd72bf3b455dabd22a0e8`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.19/oecore-2814f0962f56c8d1afa4de76d2895ba9b5cb767d.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.19/oecore-2814f0962f56c8d1afa4de76d2895ba9b5cb767d.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `scarthgap`
- Tag: `yocto-5.0.19`
- Git Revision: `2f749ae477c3b94dce71038f025180d7f612dab0`
- Release Artefact: `meta-yocto-2f749ae477c3b94dce71038f025180d7f612dab0`
- sha: `754237ee59a67d31da1f242555c77b75a96d9cdabdf0a4c9cfd98e378643d031`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.19/meta-yocto-2f749ae477c3b94dce71038f025180d7f612dab0.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.19/meta-yocto-2f749ae477c3b94dce71038f025180d7f612dab0.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `scarthgap`
- Tag: `yocto-5.0.19`
- Git Revision: `bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- Release Artefact: `meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f`
- sha: `ab073def6487f237ac125d239b3739bf02415270959546b6b287778664f0ae65`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.19/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.19/meta-mingw-bd9fef71ec005be3c3a6d7f8b99d8116daf70c4f.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.8`
- Tag: `yocto-5.0.19`
- Git Revision: `0880963fea4d91a034e4a6e007d23f98658ab986`
- Release Artefact: `bitbake-0880963fea4d91a034e4a6e007d23f98658ab986`
- sha: `2bbf83d622fd4ad7ef0110378a9c88b683b2d82a911aba681b561446ec2f486b`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.19/bitbake-0880963fea4d91a034e4a6e007d23f98658ab986.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.19/bitbake-0880963fea4d91a034e4a6e007d23f98658ab986.tar.bz2>

## 17.7.22 Release notes for Yocto-5.0.20 (Scarthgap)

### Security Fixes in Yocto-5.0.20

- binutils: Fix CVE-2025-69645, CVE-2025-69649, CVE-2025-69652 and CVE-2026-6846
- busybox: Fix CVE-2026-38754
- bzip2: Fix CVE-2026-42250
- cargo: Fix CVE-2026-5222 and CVE-2026-5223

- cups: Fix CVE-2026-27447, CVE-2026-34978, CVE-2026-34979, CVE-2026-34980, CVE-2026-34990, CVE-2026-39314, CVE-2026-39316 and CVE-2026-41079
- curl: Ignore CVE-2026-10536 if nhttp2 not enabled
- curl: Fix CVE-2026-4873, CVE-2026-5545, CVE-2026-5773, CVE-2026-6253 and CVE-2026-6276
- dhcpcd: Fix CVE-2026-56113, CVE-2026-56114 and CVE-2026-56117
- expat: Fix CVE-2026-41080, CVE-2026-45186, CVE-2026-56132, CVE-2026-56403, CVE-2026-56404, CVE-2026-56405, CVE-2026-56406, CVE-2026-56407, CVE-2026-56408, CVE-2026-56409, CVE-2026-56410 and CVE-2026-56411
- gawk: Fix CVE-2026-40467, CVE-2026-40468, CVE-2026-40469 and CVE-2026-40553
- glib-2.0: Fix CVE-2026-58010, CVE-2026-58011, CVE-2026-58012, CVE-2026-58013, CVE-2026-58014 and CVE-2026-58016
- gnutls: Fix CVE-2026-3833 and CVE-2026-42009
- gnutls: Ignore CVE-2026-3832
- gzip: Fix CVE-2026-41991 and CVE-2026-41992
- libcap: Fix CVE-2026-4878
- libpng: Fix CVE-2026-34757
- libsndfile1: Fix CVE-2026-37555
- libsolv: Fix CVE-2026-9149
- libssh2: Fix CVE-2025-15661, CVE-2026-55199, CVE-2026-55200, CVE-2026-66032, CVE-2026-66033, CVE-2026-66034 and CVE-2026-66035
- libxml2: Fix CVE-2026-11979
- libxpm: Fix CVE-2026-4367
- linux-yocto/6.6: Fix CVE-2025-23131, CVE-2025-68296, CVE-2025-68736, CVE-2025-68768, CVE-2026-23278, CVE-2026-23346, CVE-2026-31419, CVE-2026-31432, CVE-2026-31486, CVE-2026-43010, CVE-2026-43019, CVE-2026-43088, CVE-2026-43116, CVE-2026-43129, CVE-2026-43219, CVE-2026-43240, CVE-2026-43303, CVE-2026-43311, CVE-2026-43331, CVE-2026-43421, CVE-2026-45850, CVE-2026-45930, CVE-2026-46054, CVE-2026-46135, CVE-2026-46140, CVE-2026-46242, CVE-2026-46252, CVE-2026-46320, CVE-2026-46321, CVE-2026-46322, CVE-2026-46331, CVE-2026-52908, CVE-2026-52909, CVE-2026-52910, CVE-2026-52913, CVE-2026-52917, CVE-2026-52923, CVE-2026-52924, CVE-2026-52927, CVE-2026-52928, CVE-2026-52929, CVE-2026-52930, CVE-2026-52934, CVE-2026-52935, CVE-2026-52939, CVE-2026-52942, CVE-2026-52943, CVE-2026-52944, CVE-2026-52946, CVE-2026-52947, CVE-2026-52948, CVE-2026-53080, CVE-2026-53131, CVE-2026-53133, CVE-2026-53134, CVE-2026-53135, CVE-2026-53136, CVE-2026-53137, CVE-2026-53138, CVE-2026-53139, CVE-2026-53143, CVE-2026-53144, CVE-2026-53146, CVE-2026-53147, CVE-2026-53148, CVE-2026-53149, CVE-2026-53150, CVE-2026-53151, CVE-2026-53154, CVE-2026-53157, CVE-2026-53158, CVE-2026-53159, CVE-2026-53160, CVE-2026-53161, CVE-2026-53163, CVE-2026-53167, CVE-2026-53168, CVE-2026-53176, CVE-2026-53177, CVE-2026-53181, CVE-2026-53182,

CVE-2026-53183, CVE-2026-53184, CVE-2026-53185, CVE-2026-53186, CVE-2026-53189, CVE-2026-53190, CVE-2026-53194, CVE-2026-53195, CVE-2026-53196, CVE-2026-53198, CVE-2026-53199, CVE-2026-53207, CVE-2026-53208, CVE-2026-53209, CVE-2026-53212, CVE-2026-53213, CVE-2026-53214, CVE-2026-53215, CVE-2026-53216, CVE-2026-53217, CVE-2026-53218, CVE-2026-53219, CVE-2026-53221, CVE-2026-53223, CVE-2026-53225, CVE-2026-53227, CVE-2026-53228, CVE-2026-53230, CVE-2026-53232, CVE-2026-53236, CVE-2026-53237, CVE-2026-53238, CVE-2026-53239, CVE-2026-53242, CVE-2026-53245, CVE-2026-53247, CVE-2026-53249, CVE-2026-53252, CVE-2026-53253, CVE-2026-53254, CVE-2026-53255, CVE-2026-53256, CVE-2026-53263, CVE-2026-53264, CVE-2026-53265, CVE-2026-53266, CVE-2026-53267, CVE-2026-53268, CVE-2026-53269, CVE-2026-53270, CVE-2026-53271, CVE-2026-53273, CVE-2026-53274, CVE-2026-53275, CVE-2026-53325, CVE-2026-53327, CVE-2026-53329, CVE-2026-53331, CVE-2026-53336, CVE-2026-53337, CVE-2026-53339, CVE-2026-53343, CVE-2026-53345, CVE-2026-53347, CVE-2026-53349, CVE-2026-53350, CVE-2026-53352, CVE-2026-53353, CVE-2026-53354, CVE-2026-53355, CVE-2026-53356, CVE-2026-53358, CVE-2026-53359, CVE-2026-53361, CVE-2026-53362, CVE-2026-53366, CVE-2026-53381, CVE-2026-53382, CVE-2026-53383, CVE-2026-53384, CVE-2026-53385, CVE-2026-53388, CVE-2026-53390, CVE-2026-53391, CVE-2026-53397, CVE-2026-53398, CVE-2026-53403, CVE-2026-63794, CVE-2026-63795, CVE-2026-63796, CVE-2026-63797, CVE-2026-63798, CVE-2026-63800, CVE-2026-63801, CVE-2026-63802, CVE-2026-63803, CVE-2026-63804, CVE-2026-63807, CVE-2026-63808, CVE-2026-63809, CVE-2026-63812, CVE-2026-63814, CVE-2026-63817, CVE-2026-63821, CVE-2026-63822, CVE-2026-63823, CVE-2026-63824, CVE-2026-63826, CVE-2026-63827, CVE-2026-63828, CVE-2026-63830, CVE-2026-63831, CVE-2026-63833, CVE-2026-63834, CVE-2026-63835, CVE-2026-63836, CVE-2026-63867, CVE-2026-63868, CVE-2026-63870, CVE-2026-63875, CVE-2026-63876, CVE-2026-63877, CVE-2026-63881, CVE-2026-63882, CVE-2026-63883, CVE-2026-63884, CVE-2026-63886, CVE-2026-63887, CVE-2026-63888, CVE-2026-63889, CVE-2026-63890, CVE-2026-63891, CVE-2026-63892, CVE-2026-63893, CVE-2026-63895, CVE-2026-63896, CVE-2026-63897, CVE-2026-63898, CVE-2026-63899, CVE-2026-63900, CVE-2026-63901, CVE-2026-63902, CVE-2026-63903, CVE-2026-63904, CVE-2026-63905, CVE-2026-63906, CVE-2026-63908, CVE-2026-63909, CVE-2026-63912, CVE-2026-63913, CVE-2026-63914, CVE-2026-63915, CVE-2026-63916, CVE-2026-63917, CVE-2026-63919, CVE-2026-63920, CVE-2026-63921, CVE-2026-63922, CVE-2026-63924, CVE-2026-63925, CVE-2026-63926, CVE-2026-63927, CVE-2026-63928, CVE-2026-63930, CVE-2026-63931, CVE-2026-63933, CVE-2026-63934, CVE-2026-63942, CVE-2026-63943, CVE-2026-63944, CVE-2026-63945, CVE-2026-63946, CVE-2026-63947, CVE-2026-63948, CVE-2026-63949, CVE-2026-63952, CVE-2026-63954, CVE-2026-63956, CVE-2026-63957, CVE-2026-63958, CVE-2026-63959, CVE-2026-63960, CVE-2026-63961, CVE-2026-63964, CVE-2026-63967, CVE-2026-63968, CVE-2026-63969, CVE-2026-63971, CVE-2026-63973, CVE-2026-63975, CVE-2026-63976, CVE-2026-63984, CVE-2026-63985, CVE-2026-63990, CVE-2026-63991, CVE-2026-63992, CVE-2026-63993, CVE-2026-63994, CVE-2026-64000, CVE-2026-64002, CVE-2026-64003, CVE-2026-64004, CVE-2026-64005, CVE-2026-64006, CVE-2026-64007, CVE-2026-64009, CVE-2026-64010, CVE-2026-64011, CVE-2026-64012, CVE-2026-64014, CVE-2026-64026, CVE-2026-64090, CVE-2026-64091, CVE-2026-64093, CVE-2026-64094, CVE-2026-64095, CVE-2026-64109, CVE-2026-64116, CVE-2026-64123, CVE-2026-64131, CVE-2026-64137, CVE-2026-64188 and CVE-2026-64191

- **linux-yocto/6.6:** Ignore CVE-2023-52920, CVE-2024-14027, CVE-2024-27022, CVE-2024-43826, CVE-2024-46691, CVE-2024-56647, CVE-2024-58093, CVE-2025-21682, CVE-2025-21739, CVE-2025-21817, CVE-2025-22125, CVE-2025-38164, CVE-2025-38426, CVE-2025-38531, CVE-2025-38584,

CVE-2025-38704, CVE-2025-38710, CVE-2025-39748, CVE-2025-39764, CVE-2025-39930, CVE-2025-39981, CVE-2025-40135, CVE-2025-40150, CVE-2025-40219, CVE-2025-40242, CVE-2025-68206, CVE-2025-68239, CVE-2025-68315, CVE-2025-68334, CVE-2025-71152, CVE-2025-71161, CVE-2025-71184, CVE-2025-71203, CVE-2025-71221, CVE-2025-71239, CVE-2025-71265, CVE-2025-71266, CVE-2025-71267, CVE-2025-71269, CVE-2025-71274, CVE-2025-71286, CVE-2025-71287, CVE-2025-71288, CVE-2025-71291, CVE-2025-71292, CVE-2025-71295, CVE-2025-71297, CVE-2025-71303, CVE-2025-71304, CVE-2025-71305, CVE-2025-71306, CVE-2025-71307, CVE-2025-71308, CVE-2025-71309, CVE-2025-71311, CVE-2025-71312, CVE-2025-71314, CVE-2026-23004, CVE-2026-23050, CVE-2026-23053, CVE-2026-23066, CVE-2026-23118, CVE-2026-23138, CVE-2026-23154, CVE-2026-23157, CVE-2026-23171, CVE-2026-23227, CVE-2026-23231, CVE-2026-23242, CVE-2026-23243, CVE-2026-23244, CVE-2026-23245, CVE-2026-23246, CVE-2026-23253, CVE-2026-23255, CVE-2026-23268, CVE-2026-23269, CVE-2026-23270, CVE-2026-23271, CVE-2026-23272, CVE-2026-23273, CVE-2026-23274, CVE-2026-23277, CVE-2026-23279, CVE-2026-23281, CVE-2026-23284, CVE-2026-23285, CVE-2026-23286, CVE-2026-23287, CVE-2026-23289, CVE-2026-23290, CVE-2026-23291, CVE-2026-23292, CVE-2026-23293, CVE-2026-23296, CVE-2026-23298, CVE-2026-23300, CVE-2026-23302, CVE-2026-23303, CVE-2026-23304, CVE-2026-23306, CVE-2026-23307, CVE-2026-23308, CVE-2026-23309, CVE-2026-23310, CVE-2026-23312, CVE-2026-23313, CVE-2026-23315, CVE-2026-23317, CVE-2026-23318, CVE-2026-23319, CVE-2026-23321, CVE-2026-23324, CVE-2026-23325, CVE-2026-23330, CVE-2026-23334, CVE-2026-23335, CVE-2026-23336, CVE-2026-23339, CVE-2026-23340, CVE-2026-23343, CVE-2026-23347, CVE-2026-23351, CVE-2026-23352, CVE-2026-23356, CVE-2026-23357, CVE-2026-23359, CVE-2026-23360, CVE-2026-23362, CVE-2026-23364, CVE-2026-23365, CVE-2026-23367, CVE-2026-23368, CVE-2026-23370, CVE-2026-23372, CVE-2026-23374, CVE-2026-23378, CVE-2026-23379, CVE-2026-23381, CVE-2026-23382, CVE-2026-23386, CVE-2026-23387, CVE-2026-23388, CVE-2026-23389, CVE-2026-23391, CVE-2026-23392, CVE-2026-23394, CVE-2026-23395, CVE-2026-23396, CVE-2026-23397, CVE-2026-23398, CVE-2026-23399, CVE-2026-23401, CVE-2026-23403, CVE-2026-23404, CVE-2026-23405, CVE-2026-23406, CVE-2026-23407, CVE-2026-23408, CVE-2026-23409, CVE-2026-23410, CVE-2026-23411, CVE-2026-23412, CVE-2026-23413, CVE-2026-23414, CVE-2026-23419, CVE-2026-23420, CVE-2026-23422, CVE-2026-23426, CVE-2026-23427, CVE-2026-23428, CVE-2026-23434, CVE-2026-23438, CVE-2026-23439, CVE-2026-23440, CVE-2026-23441, CVE-2026-23442, CVE-2026-23443, CVE-2026-23444, CVE-2026-23446, CVE-2026-23447, CVE-2026-23448, CVE-2026-23449, CVE-2026-23450, CVE-2026-23452, CVE-2026-23454, CVE-2026-23455, CVE-2026-23456, CVE-2026-23457, CVE-2026-23458, CVE-2026-23460, CVE-2026-23461, CVE-2026-23462, CVE-2026-23463, CVE-2026-23465, CVE-2026-23468, CVE-2026-23474, CVE-2026-23475, CVE-2026-31389, CVE-2026-31391, CVE-2026-31392, CVE-2026-31393, CVE-2026-31396, CVE-2026-31399, CVE-2026-31400, CVE-2026-31402, CVE-2026-31403, CVE-2026-31405, CVE-2026-31407, CVE-2026-31408, CVE-2026-31409, CVE-2026-31411, CVE-2026-31412, CVE-2026-31414, CVE-2026-31415, CVE-2026-31416, CVE-2026-31417, CVE-2026-31418, CVE-2026-31421, CVE-2026-31422, CVE-2026-31423, CVE-2026-31424, CVE-2026-31425, CVE-2026-31426, CVE-2026-31427, CVE-2026-31428, CVE-2026-31429, CVE-2026-31430, CVE-2026-31431, CVE-2026-31433, CVE-2026-31434, CVE-2026-31439, CVE-2026-31440, CVE-2026-31441, CVE-2026-31444, CVE-2026-31446, CVE-2026-31447, CVE-2026-31448, CVE-2026-31449, CVE-2026-31450, CVE-2026-31451, CVE-2026-31452, CVE-2026-31453, CVE-2026-31454, CVE-2026-31455, CVE-2026-31458, CVE-2026-31464, CVE-2026-31466, CVE-2026-31467, CVE-2026-31469, CVE-2026-31473, CVE-2026-31474, CVE-2026-31476, CVE-2026-31477, CVE-2026-31478, CVE-2026-31480, CVE-2026-31482, CVE-2026-31483, CVE-2026-31485, CVE-2026-31488, CVE-2026-31489, CVE-2026-31492,





CVE-2026-43120, CVE-2026-43123, CVE-2026-43124, CVE-2026-43128, CVE-2026-43130, CVE-2026-43132, CVE-2026-43133, CVE-2026-43134, CVE-2026-43135, CVE-2026-43136, CVE-2026-43137, CVE-2026-43139, CVE-2026-43140, CVE-2026-43141, CVE-2026-43143, CVE-2026-43145, CVE-2026-43147, CVE-2026-43148, CVE-2026-43149, CVE-2026-43150, CVE-2026-43152, CVE-2026-43156, CVE-2026-43157, CVE-2026-43158, CVE-2026-43159, CVE-2026-43162, CVE-2026-43163, CVE-2026-43167, CVE-2026-43168, CVE-2026-43170, CVE-2026-43171, CVE-2026-43173, CVE-2026-43180, CVE-2026-43182, CVE-2026-43183, CVE-2026-43184, CVE-2026-43186, CVE-2026-43187, CVE-2026-43189, CVE-2026-43190, CVE-2026-43194 and CVE-2026-43196

- **linux-yocto/6.6: (cont.)** Ignore CVE-2026-43200, CVE-2026-43202, CVE-2026-43203, CVE-2026-43205, CVE-2026-43206, CVE-2026-43207, CVE-2026-43209, CVE-2026-43211, CVE-2026-43212, CVE-2026-43214, CVE-2026-43215, CVE-2026-43218, CVE-2026-43220, CVE-2026-43221, CVE-2026-43222, CVE-2026-43223, CVE-2026-43225, CVE-2026-43226, CVE-2026-43227, CVE-2026-43230, CVE-2026-43231, CVE-2026-43232, CVE-2026-43233, CVE-2026-43236, CVE-2026-43238, CVE-2026-43239, CVE-2026-43241, CVE-2026-43242, CVE-2026-43245, CVE-2026-43246, CVE-2026-43251, CVE-2026-43252, CVE-2026-43253, CVE-2026-43255, CVE-2026-43256, CVE-2026-43257, CVE-2026-43261, CVE-2026-43262, CVE-2026-43264, CVE-2026-43265, CVE-2026-43266, CVE-2026-43268, CVE-2026-43269, CVE-2026-43270, CVE-2026-43271, CVE-2026-43273, CVE-2026-43275, CVE-2026-43277, CVE-2026-43278, CVE-2026-43279, CVE-2026-43281, CVE-2026-43283, CVE-2026-43284, CVE-2026-43287, CVE-2026-43288, CVE-2026-43289, CVE-2026-43291, CVE-2026-43295, CVE-2026-43296, CVE-2026-43302, CVE-2026-43304, CVE-2026-43312, CVE-2026-43313, CVE-2026-43314, CVE-2026-43315, CVE-2026-43316, CVE-2026-43319, CVE-2026-43324, CVE-2026-43327, CVE-2026-43328, CVE-2026-43329, CVE-2026-43330, CVE-2026-43332, CVE-2026-43333, CVE-2026-43334, CVE-2026-43336, CVE-2026-43339, CVE-2026-43340, CVE-2026-43341, CVE-2026-43342, CVE-2026-43343, CVE-2026-43345, CVE-2026-43350, CVE-2026-43355, CVE-2026-43357, CVE-2026-43359, CVE-2026-43360, CVE-2026-43361, CVE-2026-43362, CVE-2026-43363, CVE-2026-43365, CVE-2026-43366, CVE-2026-43368, CVE-2026-43370, CVE-2026-43371, CVE-2026-43372, CVE-2026-43373, CVE-2026-43376, CVE-2026-43377, CVE-2026-43378, CVE-2026-43379, CVE-2026-43380, CVE-2026-43381, CVE-2026-43382, CVE-2026-43383, CVE-2026-43386, CVE-2026-43387, CVE-2026-43397, CVE-2026-43405, CVE-2026-43406, CVE-2026-43407, CVE-2026-43409, CVE-2026-43411, CVE-2026-43412, CVE-2026-43413, CVE-2026-43415, CVE-2026-43419, CVE-2026-43420, CVE-2026-43424, CVE-2026-43425, CVE-2026-43426, CVE-2026-43427, CVE-2026-43428, CVE-2026-43429, CVE-2026-43430, CVE-2026-43432, CVE-2026-43436, CVE-2026-43437, CVE-2026-43439, CVE-2026-43441, CVE-2026-43445, CVE-2026-43448, CVE-2026-43449, CVE-2026-43450, CVE-2026-43451, CVE-2026-43452, CVE-2026-43453, CVE-2026-43455, CVE-2026-43457, CVE-2026-43458, CVE-2026-43459, CVE-2026-43466, CVE-2026-43468, CVE-2026-43469, CVE-2026-43471, CVE-2026-43472, CVE-2026-43473, CVE-2026-43475, CVE-2026-43476, CVE-2026-43480, CVE-2026-43483, CVE-2026-43484, CVE-2026-43488, CVE-2026-43490, CVE-2026-43491, CVE-2026-43492, CVE-2026-43493, CVE-2026-43494, CVE-2026-43495, CVE-2026-43496, CVE-2026-43497, CVE-2026-43499, CVE-2026-43500, CVE-2026-43501, CVE-2026-43502, CVE-2026-43503, CVE-2026-45834, CVE-2026-45835, CVE-2026-45836, CVE-2026-45837, CVE-2026-45838, CVE-2026-45839, CVE-2026-45840, CVE-2026-45841, CVE-2026-45842, CVE-2026-45843, CVE-2026-45844, CVE-2026-45845, CVE-2026-45846, CVE-2026-45847, CVE-2026-45848, CVE-2026-45849, CVE-2026-45851, CVE-2026-45852, CVE-2026-45853, CVE-2026-45854, CVE-2026-45856, CVE-2026-45857, CVE-2026-45858, CVE-2026-45860, CVE-2026-45862, CVE-2026-45863, CVE-2026-45864, CVE-2026-45865, CVE-2026-45866, CVE-2026-45867,



46144, CVE-2026-46145, CVE-2026-46146, CVE-2026-46149, CVE-2026-46150, CVE-2026-46151, CVE-2026-46152, CVE-2026-46154, CVE-2026-46155, CVE-2026-46156, CVE-2026-46158, CVE-2026-46159, CVE-2026-46160, CVE-2026-46161, CVE-2026-46162, CVE-2026-46163, CVE-2026-46164, CVE-2026-46165, CVE-2026-46166, CVE-2026-46167, CVE-2026-46168, CVE-2026-46169, CVE-2026-46170, CVE-2026-46172, CVE-2026-46173, CVE-2026-46174, CVE-2026-46176, CVE-2026-46177, CVE-2026-46178, CVE-2026-46179, CVE-2026-46180, CVE-2026-46182, CVE-2026-46183, CVE-2026-46184, CVE-2026-46185, CVE-2026-46186, CVE-2026-46187, CVE-2026-46188, CVE-2026-46189, CVE-2026-46190, CVE-2026-46191, CVE-2026-46192, CVE-2026-46193, CVE-2026-46194, CVE-2026-46195, CVE-2026-46196, CVE-2026-46197, CVE-2026-46198, CVE-2026-46199, CVE-2026-46201, CVE-2026-46202, CVE-2026-46203, CVE-2026-46204, CVE-2026-46205, CVE-2026-46206, CVE-2026-46207, CVE-2026-46208, CVE-2026-46209, CVE-2026-46210, CVE-2026-46211, CVE-2026-46212, CVE-2026-46213, CVE-2026-46214, CVE-2026-46215, CVE-2026-46216, CVE-2026-46218, CVE-2026-46219, CVE-2026-46220, CVE-2026-46221, CVE-2026-46222, CVE-2026-46223, CVE-2026-46224, CVE-2026-46225, CVE-2026-46226, CVE-2026-46227, CVE-2026-46228, CVE-2026-46229, CVE-2026-46230, CVE-2026-46231, CVE-2026-46232, CVE-2026-46233, CVE-2026-46234, CVE-2026-46235, CVE-2026-46236, CVE-2026-46238, CVE-2026-46239, CVE-2026-46240, CVE-2026-46243, CVE-2026-46244, CVE-2026-46246, CVE-2026-46247, CVE-2026-46248, CVE-2026-46249, CVE-2026-46250, CVE-2026-46251, CVE-2026-46253, CVE-2026-46255, CVE-2026-46256, CVE-2026-46257, CVE-2026-46258, CVE-2026-46259, CVE-2026-46260, CVE-2026-46261, CVE-2026-46262, CVE-2026-46263, CVE-2026-46264, CVE-2026-46265, CVE-2026-46266, CVE-2026-46267, CVE-2026-46268, CVE-2026-46269, CVE-2026-46270, CVE-2026-46271, CVE-2026-46273, CVE-2026-46274, CVE-2026-46275, CVE-2026-46276, CVE-2026-46277, CVE-2026-46278, CVE-2026-46279, CVE-2026-46280, CVE-2026-46281, CVE-2026-46283, CVE-2026-46284, CVE-2026-46285, CVE-2026-46286, CVE-2026-46287, CVE-2026-46288, CVE-2026-46289, CVE-2026-46290, CVE-2026-46291, CVE-2026-46292, CVE-2026-46293, CVE-2026-46294, CVE-2026-46295, CVE-2026-46296, CVE-2026-46297, CVE-2026-46298 and CVE-2026-46299

- linux-yocto/6.6: (cont.) Ignore CVE-2026-46300, CVE-2026-46301, CVE-2026-46303, CVE-2026-46304, CVE-2026-46305, CVE-2026-46306, CVE-2026-46307, CVE-2026-46308, CVE-2026-46309, CVE-2026-46310, CVE-2026-46311, CVE-2026-46312, CVE-2026-46313, CVE-2026-46315, CVE-2026-46316, CVE-2026-46317, CVE-2026-46318, CVE-2026-46319, CVE-2026-46323, CVE-2026-46326, CVE-2026-46327, CVE-2026-46328, CVE-2026-46329, CVE-2026-46332, CVE-2026-46333, CVE-2026-52904, CVE-2026-52905, CVE-2026-52906, CVE-2026-52907, CVE-2026-52911, CVE-2026-52912, CVE-2026-52914, CVE-2026-52915, CVE-2026-52916, CVE-2026-52918, CVE-2026-52919, CVE-2026-52920, CVE-2026-52921, CVE-2026-52922, CVE-2026-52925, CVE-2026-52926, CVE-2026-52931, CVE-2026-52932, CVE-2026-52933, CVE-2026-52936, CVE-2026-52938, CVE-2026-52940, CVE-2026-52941, CVE-2026-52945, CVE-2026-52949, CVE-2026-52950, CVE-2026-52951, CVE-2026-52952, CVE-2026-52954, CVE-2026-52955, CVE-2026-52957, CVE-2026-52958, CVE-2026-52959, CVE-2026-52960, CVE-2026-52962, CVE-2026-52963, CVE-2026-52964, CVE-2026-52965, CVE-2026-52966, CVE-2026-52967, CVE-2026-52968, CVE-2026-52969, CVE-2026-52970, CVE-2026-52971, CVE-2026-52972, CVE-2026-52973, CVE-2026-52974, CVE-2026-52975, CVE-2026-52976, CVE-2026-52977, CVE-2026-52978, CVE-2026-52979, CVE-2026-52980, CVE-2026-52981, CVE-2026-52982, CVE-2026-52983, CVE-2026-52984, CVE-2026-52985, CVE-2026-52986, CVE-2026-52987, CVE-2026-52989, CVE-2026-52992, CVE-2026-52993, CVE-2026-52994, CVE-2026-52995, CVE-2026-52996, CVE-2026-52997, CVE-2026-52998, CVE-2026-52999, CVE-2026-53001, CVE-2026-53002, CVE-2026-53003, CVE-2026-

53004, CVE-2026-53006, CVE-2026-53007, CVE-2026-53008, CVE-2026-53011, CVE-2026-53012, CVE-2026-53013, CVE-2026-53014, CVE-2026-53016, CVE-2026-53019, CVE-2026-53020, CVE-2026-53021, CVE-2026-53022, CVE-2026-53023, CVE-2026-53026, CVE-2026-53028, CVE-2026-53029, CVE-2026-53030, CVE-2026-53031, CVE-2026-53032, CVE-2026-53033, CVE-2026-53034, CVE-2026-53035, CVE-2026-53036, CVE-2026-53037, CVE-2026-53038, CVE-2026-53039, CVE-2026-53040, CVE-2026-53041, CVE-2026-53042, CVE-2026-53043, CVE-2026-53044, CVE-2026-53045, CVE-2026-53046, CVE-2026-53047, CVE-2026-53048, CVE-2026-53049, CVE-2026-53050, CVE-2026-53051, CVE-2026-53052, CVE-2026-53054, CVE-2026-53055, CVE-2026-53056, CVE-2026-53057, CVE-2026-53058, CVE-2026-53059, CVE-2026-53060, CVE-2026-53061, CVE-2026-53062, CVE-2026-53063, CVE-2026-53064, CVE-2026-53065, CVE-2026-53066, CVE-2026-53067, CVE-2026-53068, CVE-2026-53069, CVE-2026-53071, CVE-2026-53072, CVE-2026-53073, CVE-2026-53074, CVE-2026-53075, CVE-2026-53076, CVE-2026-53077, CVE-2026-53079, CVE-2026-53081, CVE-2026-53082, CVE-2026-53083, CVE-2026-53084, CVE-2026-53085, CVE-2026-53086, CVE-2026-53087, CVE-2026-53088, CVE-2026-53092, CVE-2026-53093, CVE-2026-53094, CVE-2026-53095, CVE-2026-53096, CVE-2026-53098, CVE-2026-53099, CVE-2026-53100, CVE-2026-53101, CVE-2026-53103, CVE-2026-53104, CVE-2026-53105, CVE-2026-53107, CVE-2026-53110, CVE-2026-53111, CVE-2026-53112, CVE-2026-53114, CVE-2026-53116, CVE-2026-53117, CVE-2026-53119, CVE-2026-53121, CVE-2026-53123, CVE-2026-53124, CVE-2026-53125, CVE-2026-53126, CVE-2026-53127, CVE-2026-53128, CVE-2026-53130, CVE-2026-53140, CVE-2026-53141, CVE-2026-53142, CVE-2026-53145, CVE-2026-53152, CVE-2026-53153, CVE-2026-53155, CVE-2026-53162, CVE-2026-53164, CVE-2026-53165, CVE-2026-53169, CVE-2026-53170, CVE-2026-53171, CVE-2026-53172, CVE-2026-53173, CVE-2026-53174, CVE-2026-53175, CVE-2026-53180, CVE-2026-53187, CVE-2026-53188, CVE-2026-53191, CVE-2026-53192, CVE-2026-53193, CVE-2026-53197, CVE-2026-53200, CVE-2026-53201, CVE-2026-53202, CVE-2026-53203, CVE-2026-53204, CVE-2026-53205, CVE-2026-53206, CVE-2026-53210, CVE-2026-53211, CVE-2026-53222, CVE-2026-53231, CVE-2026-53233, CVE-2026-53234, CVE-2026-53235, CVE-2026-53240, CVE-2026-53241, CVE-2026-53243, CVE-2026-53244, CVE-2026-53248, CVE-2026-53250, CVE-2026-53251, CVE-2026-53257, CVE-2026-53259, CVE-2026-53260, CVE-2026-53261, CVE-2026-53276, CVE-2026-53277, CVE-2026-53278, CVE-2026-53279, CVE-2026-53280, CVE-2026-53281, CVE-2026-53282, CVE-2026-53283, CVE-2026-53286, CVE-2026-53287, CVE-2026-53288, CVE-2026-53289, CVE-2026-53290, CVE-2026-53291, CVE-2026-53293, CVE-2026-53294, CVE-2026-53295, CVE-2026-53296, CVE-2026-53298, CVE-2026-53299, CVE-2026-53300, CVE-2026-53301, CVE-2026-53302, CVE-2026-53303, CVE-2026-53304, CVE-2026-53305, CVE-2026-53306, CVE-2026-53307, CVE-2026-53308, CVE-2026-53309, CVE-2026-53310, CVE-2026-53311, CVE-2026-53312, CVE-2026-53314, CVE-2026-53315, CVE-2026-53316, CVE-2026-53318, CVE-2026-53319, CVE-2026-53320, CVE-2026-53321, CVE-2026-53322, CVE-2026-53323, CVE-2026-53324, CVE-2026-53326, CVE-2026-53328, CVE-2026-53333, CVE-2026-53334, CVE-2026-53335, CVE-2026-53338, CVE-2026-53340, CVE-2026-53341, CVE-2026-53342, CVE-2026-53344, CVE-2026-53346, CVE-2026-53348, CVE-2026-53351, CVE-2026-53357, CVE-2026-53360, CVE-2026-53363, CVE-2026-53364, CVE-2026-53365, CVE-2026-53367, CVE-2026-53369, CVE-2026-53370, CVE-2026-53371, CVE-2026-53372, CVE-2026-53373, CVE-2026-53374, CVE-2026-53375, CVE-2026-53376, CVE-2026-53378, CVE-2026-53379, CVE-2026-53380, CVE-2026-53386, CVE-2026-53387, CVE-2026-53389, CVE-2026-53394, CVE-2026-53395, CVE-2026-53396, CVE-2026-63793, CVE-2026-63799, CVE-2026-63813, CVE-2026-63820, CVE-2026-63832, CVE-2026-63837, CVE-2026-63838, CVE-2026-63839, CVE-2026-63840, CVE-2026-63841, CVE-2026-63842, CVE-2026-63843, CVE-2026-63844, CVE-2026-63845, CVE-2026-63846, CVE-2026-63847, CVE-2026-63848, CVE-2026-63849, CVE-2026-63850, CVE-2026-63851,

CVE-2026-63852, CVE-2026-63854, CVE-2026-63855, CVE-2026-63856, CVE-2026-63857, CVE-2026-63859, CVE-2026-63860, CVE-2026-63861, CVE-2026-63862, CVE-2026-63863, CVE-2026-63864, CVE-2026-63865, CVE-2026-63866, CVE-2026-63869, CVE-2026-63873, CVE-2026-63874, CVE-2026-63878, CVE-2026-63880, CVE-2026-63885, CVE-2026-63894, CVE-2026-63907, CVE-2026-63910, CVE-2026-63911, CVE-2026-63918, CVE-2026-63923, CVE-2026-63929, CVE-2026-63932, CVE-2026-63935, CVE-2026-63936, CVE-2026-63937, CVE-2026-63938, CVE-2026-63939, CVE-2026-63941, CVE-2026-63950, CVE-2026-63951, CVE-2026-63953, CVE-2026-63955, CVE-2026-63965, CVE-2026-63966, CVE-2026-63970, CVE-2026-63972, CVE-2026-63977, CVE-2026-63980, CVE-2026-63981, CVE-2026-63982, CVE-2026-63986, CVE-2026-63987, CVE-2026-63988, CVE-2026-63989, CVE-2026-63995, CVE-2026-63996, CVE-2026-63997, CVE-2026-63998, CVE-2026-64008, CVE-2026-64013, CVE-2026-64015, CVE-2026-64016, CVE-2026-64018, CVE-2026-64019, CVE-2026-64020, CVE-2026-64021, CVE-2026-64022, CVE-2026-64023, CVE-2026-64024, CVE-2026-64025, CVE-2026-64027, CVE-2026-64028, CVE-2026-64029, CVE-2026-64030, CVE-2026-64031, CVE-2026-64032, CVE-2026-64033, CVE-2026-64034, CVE-2026-64035, CVE-2026-64037, CVE-2026-64039, CVE-2026-64040, CVE-2026-64041, CVE-2026-64042, CVE-2026-64043, CVE-2026-64044, CVE-2026-64045, CVE-2026-64046, CVE-2026-64047, CVE-2026-64048, CVE-2026-64049, CVE-2026-64050, CVE-2026-64051, CVE-2026-64052, CVE-2026-64053, CVE-2026-64054, CVE-2026-64055, CVE-2026-64056, CVE-2026-64057, CVE-2026-64058, CVE-2026-64059, CVE-2026-64061, CVE-2026-64062, CVE-2026-64063, CVE-2026-64064, CVE-2026-64065, CVE-2026-64066, CVE-2026-64067, CVE-2026-64068, CVE-2026-64069, CVE-2026-64071, CVE-2026-64072, CVE-2026-64073, CVE-2026-64074, CVE-2026-64075, CVE-2026-64080, CVE-2026-64081, CVE-2026-64083, CVE-2026-64084, CVE-2026-64085, CVE-2026-64086, CVE-2026-64087, CVE-2026-64088, CVE-2026-64089, CVE-2026-64092, CVE-2026-64096, CVE-2026-64097, CVE-2026-64098, CVE-2026-64099, CVE-2026-64100, CVE-2026-64101, CVE-2026-64102, CVE-2026-64103, CVE-2026-64104, CVE-2026-64105, CVE-2026-64106, CVE-2026-64107, CVE-2026-64108, CVE-2026-64110, CVE-2026-64111, CVE-2026-64113, CVE-2026-64114, CVE-2026-64115, CVE-2026-64118, CVE-2026-64119, CVE-2026-64120, CVE-2026-64121, CVE-2026-64122, CVE-2026-64124, CVE-2026-64125, CVE-2026-64126, CVE-2026-64127, CVE-2026-64128, CVE-2026-64129, CVE-2026-64130, CVE-2026-64132, CVE-2026-64133, CVE-2026-64134, CVE-2026-64135, CVE-2026-64136, CVE-2026-64139, CVE-2026-64140, CVE-2026-64141, CVE-2026-64142, CVE-2026-64143, CVE-2026-64144, CVE-2026-64145, CVE-2026-64147, CVE-2026-64148, CVE-2026-64149, CVE-2026-64150, CVE-2026-64151, CVE-2026-64152, CVE-2026-64153, CVE-2026-64155, CVE-2026-64156, CVE-2026-64157, CVE-2026-64158, CVE-2026-64159, CVE-2026-64161, CVE-2026-64162, CVE-2026-64163, CVE-2026-64164, CVE-2026-64165, CVE-2026-64166, CVE-2026-64167, CVE-2026-64168, CVE-2026-64169, CVE-2026-64170, CVE-2026-64171, CVE-2026-64172, CVE-2026-64173, CVE-2026-64174, CVE-2026-64175, CVE-2026-64176, CVE-2026-64177, CVE-2026-64178, CVE-2026-64179, CVE-2026-64180, CVE-2026-64181, CVE-2026-64182, CVE-2026-64183, CVE-2026-64184, CVE-2026-64185, CVE-2026-64186 and CVE-2026-64207

- openssh: Fix CVE-2026-59995, CVE-2026-59996, CVE-2026-59997, CVE-2026-59999, CVE-2026-60000, CVE-2026-60001 and CVE-2026-60002
- openssh: Ignore CVE-2026-59998 if kerberos not enabled
- openssh: Ignore CVE-2026-3497
- perl: Fix CVE-2026-8376
- python3: Fix CVE-2026-7210, CVE-2026-9669, CVE-2026-11940 and CVE-2026-11972

- python3-setuptools: Fix [CVE-2026-59890](#)
- python3-urllib3: Fix [CVE-2026-44431](#)
- qemu: Fix [CVE-2025-14876](#), [CVE-2026-0665](#) and [CVE-2026-2243](#)
- socat: Fix [CVE-2026-56123](#)
- sqlite3: Fix [CVE-2026-11822](#) and [CVE-2026-11824](#)
- tar: Fix [CVE-2026-5704](#)
- util-linux: Fix [CVE-2026-13595](#)
- vim: Fix [CVE-2026-28417](#), [CVE-2026-28420](#), [CVE-2026-28421](#), [CVE-2026-28422](#), [CVE-2026-32249](#), [CVE-2026-34714](#), [CVE-2026-34982](#), [CVE-2026-35177](#), [CVE-2026-41411](#), [CVE-2026-42307](#), [CVE-2026-43961](#), [CVE-2026-44656](#), [CVE-2026-45130](#), [CVE-2026-46483](#), [CVE-2026-47162](#), [CVE-2026-47167](#), [CVE-2026-52858](#), [CVE-2026-52859](#) and [CVE-2026-52860](#)

### Fixes in Yocto-5.0.20

- bind: Upgrade to 9.18.49
- binutils: [CVE-2025-69648](#).patch also fixed [CVE-2025-69646](#)
- bitbake.rst: rename section to "BitBake User Manual"
- bitbake: README: Add "2.8" subject-prefix to git-send-email suggestion
- bitbake: utils: Add NFS EEXIST/isdirent failure workaround
- build-appliance-image: Update to scarthgap head revision
- bzip2: fix 'bzip2 --version > /tmp/aaa 2>&1' hang
- ca-certificates: upgrade to 20260601
- cargo-update-recipe-crates: Don't fail for partially empty Cargo.lock
- contributor-guide/identify-component.rst: use the same tense as other section
- contributor-guide: Note patch complexity requirements for stable branches
- create-spdx-image-3.0: correct `SSTATE_SKIP_CREATION` key for `do_create_image_sbom_spdx`
- cve-update: Avoid NFS caching issues
- dev-manual/sbom.rst: refresh for SPDX3
- docs: fix broken path links
- docs: fix manual names in cross references
- docs: fix various broken links
- docs: index.rst: add introduction paragraphs
- docs: index.rst: move external links to the bottom of the intro section
- docs: index.rst: move release notes in their own section
- docs: index.rst: move the "Overview and Concepts" manual in the "Introduction and Overview" section

- docs: index.rst: move the contributor guide out of the Manuals section
- docs: index.rst: show the intro paragraph only for html-based docs
- docs: kernel-dev/common.rst: remove taskhash mismatch note
- docs: README: update instructions for installing vale and sphinx-lint
- docs: recipe-style-guide: Clarify when License-Update tag is needed
- docs: remove CROPS references
- flex: update *CVE\_PRODUCT*
- glibc-testsuite: Do not generate *SPDX*
- glibc: stable 2.39 branch updates
- libgcrypt: upgrade to 1.10.4
- linux-yocto/6.6: update to v6.6.147
- migration-guide: add release notes for 5.0.19
- migration-guides/release-notes-3.4.2.rst: fix a broken link
- migration-guides/release-notes-5.0.rst: remove broken link
- migration-guides: replace broken link with archive links
- openssh: CVE-2026-35387.patch also fixed *CVE-2026-35414*
- overview-manual: move the intro content in the index
- package.bbclass: hardcode emit\_pkgdata to run last
- perf: drop newt from tui build requirements
- poky.conf: Bump version for 5.0.20 release
- python3-certifi: set *CVE\_PRODUCT*
- python3-cryptography: set *CVE\_PRODUCT*
- python3-idna: set *CVE\_PRODUCT*
- python3-pip: set *CVE\_PRODUCT*
- python3-ply: set *CVE\_PRODUCT*
- python3-pyasn1: set *CVE\_PRODUCT*
- python3-pyopenssl: set *CVE\_PRODUCT*
- python3-pyyaml: set *CVE\_PRODUCT*
- python3-xmltodict: set *CVE\_PRODUCT*
- python3: Simplify ptest exclusion list
- python3: skiptest tracemalloc\_track\_race
- ref-manual/classes.rst: replace obsolete mailing list thread



- ref-manual/features.rst: fix some cross references
- ref-manual/images.rst: update obsolete VMWare links
- ref-manual/release-process.rst: update LTS supported versions
- ref-manual: Fix occurrences of omitted space with :prepend
- ref-manual: remove all traces of "kernel\_menuconfig" task
- rootfs: move tasks using image\_list\_installed\_packages to postuninstall
- scripts/install-buildtools: Update to 5.0.19
- shadow: set *CVE\_PRODUCT*
- sudo: fix pam-wheel sed for sudo 1.9.17p2 sudoers
- sudo: set *CVE\_PRODUCT*
- tzdata/tzcode-native: upgrade 2026b -> 2026c
- u-boot: Set *CVE\_PRODUCT*
- vex: remove obsolete semicolon
- wic: Fix updating fstab for nvme devices
- wireless-regdb: upgrade to 2026.05.30
- xmlto: update *SRC\_URI*
- xserver-org: update *CVE\_PRODUCT*

### Known Issues in Yocto-5.0.20

- N/A

### Contributors to Yocto-5.0.20

Thanks to the following people who contributed to this release:

- Adarsh Jagadish Kamini
- Aleksandar Nikolic
- Alexander Kanavin
- Amaury Couderc
- Anil Dongare
- Ankur Tyagi
- Antonin Godard
- AshishKumar Mishra
- Ashishkumar Parmar
- Benjamin Robin (Schneider Electric)
- Bruce Ashfield



- Daiane Angolini
- Daniel Turull
- Darsh Kelaiya
- David Nyström
- Deepak Rathore
- Devansh Patel
- Enoch Ng
- Eric Meyers
- Esa Jaaskela
- Harish Sadineni
- Himanshu Jadon
- Hitendra Prajapati
- Hongxu Jia
- Hugo SIMELIERE (Schneider Electric)
- Jaipaul Cheernam
- Jakub Szczudlo
- Joshua Watt
- João Marcos Costa
- Kris Gavvala
- Lee Chee Yang
- Maik Otto
- Marta Rybczynska
- Martin Schwan
- Mathieu Dubois-Briand
- Nate Kent
- Niko Mauno
- Paul Barker
- Peter Marko
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Roland Kovacs

- Ross Burton
- Shubham Pushpkar
- Siddharth Doshi
- Sudhir Dumbhare
- Theo Gaige
- Theo Gaige (Schneider Electric)
- Vijay Anusuri
- Yoann Congal
- mark.yang

## Repositories / Downloads for Yocto-5.0.20

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.20](#)
- Git Revision: [fe46d5de41930a2762a9ad2543d50e0f4e10463b](#)
- Release Artefact: [yocto-docs-fe46d5de41930a2762a9ad2543d50e0f4e10463b](#)
- sha: [aae57cc7fce4c3d06a24206c939b614d55fe7dc41e0525e88282ab7ae9c429d5](#)
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.20/yocto-docs-fe46d5de41930a2762a9ad2543d50e0f4e10463b.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.20/yocto-docs-fe46d5de41930a2762a9ad2543d50e0f4e10463b.tar.bz2>

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [scarthgap](#)
- Tag: [yocto-5.0.20](#)
- Git Revision: [64e69ed23703f6358ec431d3f5f1f8483f974cae](#)
- Release Artefact: [poky-64e69ed23703f6358ec431d3f5f1f8483f974cae](#)
- sha: [533b0bbe168d5e8cfd0b58b8bff75d6110a85d3dae8e6828871868254257f762](#)
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.20/poky-64e69ed23703f6358ec431d3f5f1f8483f974cae.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.20/poky-64e69ed23703f6358ec431d3f5f1f8483f974cae.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: scarthgap
- Tag: yocto-5.0.20
- Git Revision: 70dc15941dd33270a92d1001174efb3093e79bdf
- Release Artefact: oecore-70dc15941dd33270a92d1001174efb3093e79bdf
- sha: 3025900891f488349cc2e5327b0c57287a28eca398970c691000075b54c6556f
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.20/oecore-70dc15941dd33270a92d1001174efb3093e79bdf.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.20/oecore-70dc15941dd33270a92d1001174efb3093e79bdf.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: scarthgap
- Tag: yocto-5.0.20
- Git Revision: 961c2399d06fbd04ee27d06079e186d2c4a14ad
- Release Artefact: meta-yocto-961c2399d06fbd04ee27d06079e186d2c4a14ad
- sha: a51ccee6d11696703faf8f154a44a5ceb71c3be08b6565158ad8cae0a71c9939
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.20/meta-yocto-961c2399d06fbd04ee27d06079e186d2c4a14ad.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.20/meta-yocto-961c2399d06fbd04ee27d06079e186d2c4a14ad.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: scarthgap
- Tag: yocto-5.0.20
- Git Revision: a2065f321a3dbca1e69f070502917c76653d9105
- Release Artefact: meta-mingw-a2065f321a3dbca1e69f070502917c76653d9105
- sha: 02042144a265ca5a25a8345688bb626636639a96f33d2b7b8c581edcf2d8df4e

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.20/meta-mingw-a2065f321a3dbca1e69f070502917c76653d9105.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.20/meta-mingw-a2065f321a3dbca1e69f070502917c76653d9105.tar.bz2>

bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.8
- Tag: yocto-5.0.20
- Git Revision: `cff3be6f664f8f07a40727ff63eeeb24d6f5e00b`
- Release Artefact: `bitbake-cff3be6f664f8f07a40727ff63eeeb24d6f5e00b`
- sha: `42622a37bc52f7fe9921e943026d73316cc2e8d62535e41bc4d308318c4a706e`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-5.0.20/bitbake-cff3be6f664f8f07a40727ff63eeeb24d6f5e00b.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-5.0.20/bitbake-cff3be6f664f8f07a40727ff63eeeb24d6f5e00b.tar.bz2>

## 17.8 Release 4.3 (nanbield)

### 17.8.1 Release 4.3 (nanbield)

#### Migration notes for 4.3 (nanbield)

This section provides migration information for moving to the Yocto Project 4.3 Release (codename "nanbield") from the prior release.

#### Supported kernel versions

The `OLDEST_KERNEL` setting has been changed to "5.15" in this release, meaning that out the box, older kernels are not supported. There were two reasons for this. Firstly it allows glibc optimisations that improve the performance of the system by removing compatibility code and using modern kernel APIs exclusively. The second issue was this allows 64 bit time support even on 32 bit platforms and resolves Y2038 issues.

It is still possible to override this value and build for older kernels, this is just no longer the default supported configuration. This setting does not affect which kernel versions SDKs will run against and does not affect which versions of the kernel can be used to run builds.

## Layername override implications

Code can now know which layer a recipe is coming from through the newly added `FILE_LAYERNAME` variable and the `layer-<layername> override`. This is being used for enabling QA checks on a per layer basis. For existing code this has the side effect that the QA checks will apply to recipes being bbappended from other layers - for example, patches added through such bbappends will now need to have the "Upstream-Status" specified in the patch header.

## Compiling changes

- Code on 32 bit platforms is now compiled with largefile support and 64 bit `time_t`, to avoid the Y2038 time overflow issue. This breaks the ABI and could break existing programs in untested layers.

## Supported distributions

This release supports running BitBake on new GNU/Linux distributions:

- Ubuntu 22.10
- Fedora 38
- Debian 12
- CentOS Stream 8
- AlmaLinux 8.8
- AlmaLinux 9.2

On the other hand, some earlier distributions are no longer supported:

- Fedora 36
- AlmaLinux 8.7
- AlmaLinux 9.1

See *all supported distributions*.

## edgerouter machine removed

The `edgerouter` reference BSP for the MIPS architecture in `meta-yocto-bsp` has been removed as the hardware has been unavailable for some time. There is no suitable reference MIPS hardware to replace it with, but the MIPS architecture will continue to get coverage via QEMU build/boot testing.

## Go language changes

- Support for the Glide package manager has been removed, as `go mod` has become the standard.

### systemd changes

Upstream systemd is now more strict on filesystem layout and the `usrmerge` feature is therefore required alongside systemd. The Poky test configurations have been updated accordingly for systemd.

### Recipe changes

- Runtime testing of `pptest` now fails if no test results are returned by any given `pptest`.

### Deprecated variables

The following variables have been deprecated:

- `CVE_CHECK_IGNORE`: use `CVE_STATUS` instead.

### Removed variables

The following variables have been removed:

- `AUTHOR`
- `PERLARCH`
- `PERLVERSION`
- `QEMU_USE_SLIRP` - add `slirp` to `TEST_RUNQEMUPARAMS` instead.
- `SERIAL_CONSOLES_CHECK` - no longer necessary because all consoles listed in `SERIAL_CONSOLES` are checked for their existence before a `getty` is started.

### Removed recipes

The following recipes have been removed in this release:

- `apmd`: obsolete (`apm` in `MACHINE_FEATURES` also removed).
- `cve-update-db-native`: functionally replaced by `cve-update-nvd2-native`
- `gcr3`: no longer needed by core recipes, moved to meta-gnome (`gcr`, i.e. version 4.x, is still provided).
- `glide`: as explained in *Go language changes*.
- `libdmx`: obsolete
- `linux-yocto` version 5.15 (versions 6.1 and 6.5 provided instead).
- `python3-async`: obsolete - no longer needed by `python3-gitdb` or any other core recipe
- `rust-hello-world`: there are sufficient other Rust recipes and test cases such that this is no longer needed.

### Removed classes

The following classes have been removed in this release:

- `glide`: as explained in *Go language changes*.

## Output file naming changes

In 4.3 there are some minor differences in image and SDK output file names. If you rely on the existing naming (e.g. in external scripts) you may need to either modify configuration or adapt to the new naming. Further details:

- *IMAGE\_NAME* and *IMAGE\_LINK\_NAME* now include the *IMAGE\_NAME\_SUFFIX* value directly. In practical terms, this means that `.rootfs` will now appear in image output file names. If you do not wish to have the `.rootfs` suffix used, you can just set *IMAGE\_NAME\_SUFFIX* to "" and this will now be consistently respected in both the image file and image file symlink names. As part of this change, support for the `imgsuffix` task varflag has been dropped (mostly an internal implementation detail, but if you were implementing a custom image construction with a task in a similar manner to `do_bootimg` you may have been using this).
- *SDK\_NAME* now includes the values of *IMAGE\_BASENAME* and *MACHINE* so that they are unique when building SDKs for different images and machines.

## Versioning changes

- *PR* values have been removed from all core recipes - distro maintainers who make use of *PR* values would need to curate these already so the sparsely set base values would not be that useful anymore. If you have been relying on these (i.e. you are maintaining a binary package feed where package versions should only ever increase), double-check the output (perhaps with the help of the *buildhistory* class) to ensure that package versions are consistent.
- The *PR* value can no longer be set from the recipe file name - this was rarely used, but in any case is no longer supported.
- *PE* and *PR* are no longer included in the work directory path (*WORKDIR*). This may break some tool assumptions about directory paths, but those should really be querying paths from the build system (or not poking into *WORKDIR* externally).
- Source revision information has been moved from *PV* to *PKGVS*. The user visible effect of this change is that *PV* will no longer have revision information in it and this will now be appended to the *PV* value through *PKGVS* when the packages are written out (as long as "+" is present in the *PKGVS* value). Since *PV* is used in *STAMP* and *WORKDIR*, you may notice small directory naming and stamp naming changes.
- The *SRCPV* variable is no longer needed in *PV*, but since the default *SRCPV* value is now "", using it is effectively now just a null operation - you can remove it (leaving behind the "+") , but it is not yet required to do so.

## QEMU changes

- The `runqemu` script no longer systematically adds two serial ports (`--serial null` and `-serial mon:stdio`) to the QEMU emulated machine if the user already adds such ports through the `QB_OPT_APPEND` setting.

If the user adds one port, only `--serial null` is added, and `-serial mon:stdio` is no longer passed. If the user adds more than one port, `--serial null` is no longer added either. This can break some existing QEMU based configurations expecting such serial ports to be added when `runqemu` is executed.

This change was made to avoid exceeding two serial ports, which interferes with automated testing.

- `runqemu` now uses the `ip tuntap` command instead of `tunctl`, and thus `tunctl` is no longer built by the `qemu-helper-native` recipe; if for some reason you were calling `tunctl` directly from your own scripts you should switch to calling `ip tuntap` instead.

### Miscellaneous changes

- The `-crosssdk` suffix and any `MLPREFIX` were removed from `virtual/XXX` provider/dependencies where a `PREFIX` was used as well, as we don't need both and it made automated dependency rewriting unnecessarily complex. In general this only affects internal toolchain dependencies so isn't end user visible, but if for some reason you have custom classes or recipes that rely upon the old providers then you will need to update those.

## 17.8.2 Release notes for 4.3 (nanbield)

### New Features / Enhancements in 4.3

- Linux kernel 6.5 and 6.1, gcc 13, glibc 2.38, LLVM 17, and over 300 other recipe upgrades
- The autobuilder's shared-state artefacts are now available over the [jsDelivr](#) Content Delivery Network (CDN). See `SSTATE_MIRRORS`.
- New variables:
  - `CVE_CHECK_STATUSMAP`, `CVE_STATUS`, `CVE_STATUS_GROUPS`, replacing the deprecated `CVE_CHECK_IGNORE`.
  - `FILE_LAYERNAME`: bitbake now sets this to the name of the layer containing the recipe
  - `FIT_ADDRESS_CELLS` and `UBOOT_FIT_ADDRESS_CELLS`. See details below.
  - `KERNEL_DTBDEST`: directory where to install DTB files.
  - `KERNEL_DTBVENDORED`: whether to keep vendor subdirectories.
  - `KERNEL_LOCALVERSION`: to add a string to the kernel version information.
  - `KERNEL_STRIP`: to specify the command to strip the kernel binary.
  - `LICENSE_FLAGS_DETAILS`: add extra details about a recipe license in case it is not allowed by `LICENSE_FLAGS_ACCEPTED`.
  - `MESON_TARGET`: to compile a specific Meson target instead of the default ones.
  - `OEQA_REPRODUCIBLE_TEST_PACKAGE`: to restrict package managers used in reproducibility testing.
- Layername functionality available through overrides

Code can now know which layer a recipe is coming from through the newly added `FILE_LAYERNAME` variable. This has been added as an override of the form `layer-<layername>`. In particular, this means QA checks can now be layer specific, for example:

```
ERROR_QA:layer-core:append = " patch-status"
```

This will enable the `patch-status` QA check for the core layer.

- Architecture-specific enhancements:



- RISC-V support is now enabled in LLVM 17.
- Loongarch support in the *linuxloader* class and `core-image-minimal-initramfs` image.
- The `arch-armv8` and `arch-armv9` architectures are now given Scalable Vector Extension (SVE) based tune options. Commits: [1](#), [2](#).
- Many changes to support 64-bit `time_t` on 32-bit architectures
- Kernel-related enhancements:
  - The default kernel is the current stable (6.5), and there is also support for the latest long-term release (6.1).
  - The list of fixed kernel CVEs is updated regularly using data from [linuxkernelcves.com](#).
  - A `showconfig` task was added to the *cml1* class, to easily examine the final generated `.config` file.
- New core recipes:
  - *appstream*: a collaborative effort for making machine-readable software metadata easily available (from meta-oe)
  - *cargo-c-native*: cargo applet to build and install C-ABI compatible dynamic and static libraries
  - *libadwaita*: Building blocks for modern GNOME applications (from meta-gnome)
  - *libtraceevent*: API to access the kernel tracefs directory (from meta-openembedded)
  - *libxmlb*: A library to help create and query binary XML blobs (from meta-oe)
  - *musl-legacy-error*: `glibc error()` API implementation still needed by a few packages.
  - *python3-beartype*, unbearably fast runtime type checking in pure Python.
  - *python3-booleanpy*: Define boolean algebras, create and parse boolean expressions and create custom boolean DSL (from meta-python)
  - *python3-calver*: Setuptools extension for CalVer package versions
  - *python3-click*: A simple wrapper around `optparse` for powerful command line utilities (from meta-python)
  - *python3-dtc*: Python Library for the Device Tree Compiler (from meta-virtualization)
  - *python3-isodate*: ISO 8601 date/time parser (from meta-python)
  - *python3-license-expression*: Utility library to parse, compare, simplify and normalize license expressions (from meta-python)
  - *python3-rdfliib*: a pure Python package for working with RDF (from meta-python)
  - *python3-spx-tools*, tools for SPDX validation and conversion.
  - *python3-trove-classifiers*: Canonical source for classifiers on PyPI ([pypi.org](#))
  - *python3-uritools*, replacement for the `urllib.parse` module.
  - *python3-xmltodict*: Makes working with XML feel like you are working with JSON (from meta-python)

- `ttyrun`, starts `getty` programs only when a terminal exists, preventing respawns through the `init` program. This enabled removing the `SERIAL_CONSOLES_CHECK` variable.
- `vulkan-validation-layers`: Khronos official validation layers to assist in verifying that applications correctly use the [Vulkan API](#).
- `xcb-util-cursor`: XCB port of `libXcursor` (from `meta-oe`)
- QEMU / `runqemu` enhancements:
  - QEMU has been upgraded to version 8.1
  - Many updates to the `runqemu` command.
  - The `qemu-system-native` recipe is now built with PNG support, which could be useful to grab screenshots for error reporting purposes.
- Rust improvements:
  - Rust has been upgraded to version 1.70
  - New `ptest-cargo` class was added to allow Cargo based recipes to easily add ptests
  - New `cargo_c` class was added to allow recipes to make Rust code available to C and C++ programs. See `meta-selftest/recipes-devtools/rust/rust-c-lib-example_git.bb` for an example.
- wic Image Creator enhancements:
  - `bootimg-efi`: if `fixed-size` is set then use that for `mkdosfs`
  - `bootimg-efi`: stop hardcoding VMA offsets, as required by `systemd-boot v254` (and `dracut/ukify`)
  - `bootimg-pcbios`: use kernel name from `KERNEL_IMAGETYPE` instead of hardcoding `vmlinuz`
  - Added new `gpt-hybrid` option to `ptable_format` (formatting a disk with a hybrid MBR and GPT partition scheme)
  - Use `part_name` in default imager when defined
  - Added `--hidden` argument to default imager to avoid MS Windows prompting to format partition after flashing to a USB stick/SD card
- FIT image related improvements:
  - New `FIT_ADDRESS_CELLS` and `UBOOT_FIT_ADDRESS_CELLS` variables allowing to specify 64 bit addresses, typically for loading U-Boot.
  - Added `compatible` line to config section (with value from `dtb`) to allow bootloaders to select the best matching configuration.
- SDK-related improvements:
  - Extended the following recipes to `nativesdk`: `libwebp`, `python3-ply`
- Testing:
  - The `insane` class now adds an `unimplemented-ptest` infrastructure to detect package sources with unit tests but no implemented ptests in the recipe.
  - A new task to perform recipe-wide QA checks was added: `do_recipe_qa`.

- New build-time checks for set *SUMMARY*, *HOMEPAGE*, and *RECIPE\_MAINTAINER* fields was added, and enabled for the core recipes.
- The `parselogs` runtime test was rewritten. Notably it no longer uses regular expressions, which may mean custom patterns need updating.
- A self-test to validate that the *SPDX* manifests generated by image builds are valid was added.
- The `QEMU_USE_SLIRP` variable has been replaced by adding `slirp` to `TEST_RUNQEMUPARAMS`.
- Utility script changes:
  - New `scripts/patchtest` utility to check patches to the OpenEmbedded-Core project. See *Validazione delle Patch con Patchtest* for details.
  - `scripts/bblock` was added, allowing the user to lock/unlock specific recipes from being built. This makes it possible to work on the `python3` recipe without causing `python3-native` to rebuild.
- BitBake improvements:
  - A fetcher for the Google Cloud Platform (`gs://`) was added.
  - The BitBake Cooker log now contains notes when the caches are invalidated which is useful for memory resident BitBake debugging.
  - BitBake no longer watches files with `inotify` for changes, as under load this can lead to races causing build instability.
  - Toaster's dependencies were upgraded to current releases, specifically to Django 4.2.
- Packaging changes:
  - *FILES* now accepts a `**` wildcard, which matches zero or more subdirectories.
  - The X server packagegroup now defaults to using the `modesetting` X driver, which obsoletes the `fbdev` driver.
  - If a recipe uses *LICENSE\_FLAGS* and the licenses are not accepted, it can set a custom message with *LICENSE\_FLAGS\_DETAILS* to be displayed to the users.
  - Recipes that fetch specific revisions no longer need to explicitly add *SRCPV* to *PV* as BitBake will now automatically add the revision information to *PKGVS* if needed (as long as "+" is still present in the *PKGVS* value, which is set from *PV* by default).
  - The default *PR* values in many recipes have been removed.
- Security improvements:
  - Most repositories now include a *SECURITY.md* file with hints for security researchers and other parties who might report potential security vulnerabilities.
- Prominent documentation updates:
  - New *Guida per i Collaboratori di Yocto Project e di OpenEmbedded* document.
  - New "Dealing with Vulnerability Reports" chapter in the Development Tasks Manual.
  - Long overdue documentation for the *devicetree* class.
  - New *summary about available init systems*.

- New documentation for the *uboot-sign* class and its variables and for the *kernel-devicetree* class variables.
- Miscellaneous changes:
  - Selecting systemd via *INIT\_MANAGER* now adds *usrmerge* to *DISTRO\_FEATURES* as current versions of systemd now require merged */usr*.
  - Generation of *SPDX* manifests is now enabled by default.
  - Git based recipes in OE-Core which used the *git* protocol have been changed to use *https* where possible, as it is typically faster and more reliable.
  - The *os-release* recipe added a *CPE\_NAME* to the fields provided, with the default being populated from *DISTRO*.
  - The *psplash* recipe now accepts a PNG format image through *SPLASH\_IMAGES*, instead of a harder to generate and modify *.h* file.
  - The `;` character is no longer needed to separate functions specified in *IMAGE\_POSTPROCESS\_COMMAND*, *IMAGE\_PREPROCESS\_COMMAND*, *POPULATE\_SDK\_POST\_HOST\_COMMAND*, *ROOTFS\_POSTINSTALL\_COMMAND* etc. (If any are present they will be replaced with spaces, so existing metadata does not yet need to be changed.)
  - In the *Upstream-Status* field in a patch header, "Accepted" is no longer a valid value since it is logically the same as "Backport". Change any values you have (particularly in patches applied through *bbappends* for core recipes, since they will be validated as indicated above).

### Known Issues in 4.3

- N/A

### Recipe License changes in 4.3

The following corrections have been made to the *LICENSE* values set by recipes:

- *glib-networking*: make *LICENSE* more accurate (*LGPL-2.1* -> *LGPL-2.1-or-later*) and add an exception for linking to *OpenSSL* if it is enabled (*openssl* is in *PACKAGECONFIG*)
- *libbsd*: set per-package licensing to clarify that *BSD-4-Clause* code is only in the *-doc* package
- *openssh*: *BSD-4-Clause* code has been removed completely from the codebase as part of 9.4p1 update - previously in the kirkstone release, *BSD-4-Clause* was removed from the *LICENSE* value in our recipe, however some *BSD-4-Clause* code actually still remained upstream until 9.4p1.
- *python3-sphinx*: remove *BSD-3-Clause* from *LICENSE* - *BSD-3-Clause* code was removed as part of the *python3-sphinx* 7.0.1 release (see [this upstream commit](#))

### Security Fixes in 4.3

- *bind*: [CVE-2023-2911](#), [CVE-2023-2828](#), [CVE-2023-3341](#), [CVE-2023-4236](#)
- *binutils*: [CVE-2023-1972](#)
- *connman*: [CVE-2023-28488](#)
- *cups*: [CVE-2023-32324](#), [CVE-2023-34241](#), [CVE-2023-4504](#)

- dbus: CVE-2023-34969
- dmidecode: CVE-2023-30630
- dropbear: CVE-2023-36328
- erofs-utils: CVE-2023-33551, CVE-2023-33552
- gcc: CVE-2023-4039
- ghostscript: CVE-2023-28879, CVE-2023-36664, CVE-2023-38559; ignore CVE-2023-38560
- git: CVE-2023-25652, CVE-2023-29007
- glibc: CVE-2023-4527, CVE-2023-4806
- go: CVE-2023-24537, CVE-2023-39325
- gstreamer: CVE-2023-40475, CVE-2023-40476
- inetutils: CVE-2023-40303
- libarchive: ignore CVE-2023-30571
- librsvg: CVE-2023-38633
- libwebp: CVE-2023-1999, CVE-2023-4863
- libx11: CVE-2023-3138, CVE-2023-43785, CVE-2023-43786, CVE-2023-43787
- libxml2: CVE-2023-28484, CVE-2023-29469; ignore disputed CVE-2023-45322
- libxpm: CVE-2023-43788, CVE-2023-43789, CVE-2022-44617
- linux: update CVE exclusions
- ncurses: CVE-2023-29491
- nghttp2: CVE-2023-44487
- ninja: ignore CVE-2021-4336, wrong ninja
- openssh: CVE-2023-38408
- openssl: CVE-2023-2650, CVE-2023-1255, CVE-2023-0466, CVE-2023-0465, CVE-2023-0464, CVE-2023-3817, CVE-2023-3446, CVE-2023-2975, CVE-2023-4807
- perl: CVE-2023-31484, CVE-2023-31486
- pixman: ignore CVE-2023-37769
- procps: CVE-2023-4016
- python3-git: CVE-2023-41040
- python3: ignore CVE-2023-36632
- python3-urllib3: CVE-2023-43804
- qemu: CVE-2023-40360, CVE-2023-42467; ignore CVE-2023-0664 (Windows-specific), ignore CVE-2023-2680 (RHEL specific)
- screen: CVE-2023-24626

- shadow: [CVE-2023-29383](#)
- sqlite3: ignore [CVE-2023-36191](#)
- sysstat: [CVE-2023-33204](#)
- tiff: [CVE-2022-4645](#), [CVE-2023-2731](#), [CVE-2023-26965](#), [CVE-2023-40745](#), [CVE-2023-41175](#)
- vim: [CVE-2023-2426](#), [CVE-2023-2609](#), [CVE-2023-2610](#), [CVE-2023-3896](#), [CVE-2023-5441](#), [CVE-2023-5535](#)
- zlib: ignore [CVE-2023-45853](#)

### Recipe Upgrades in 4.3

- acpica: upgrade 20220331 -> 20230628
- adwaita-icon-theme: 43 -> 45.0
- alsa-lib: upgrade 1.2.8 -> 1.2.10
- alsa-ucm-conf: upgrade 1.2.8 -> 1.2.10
- alsa-utils: upgrade 1.2.8 -> 1.2.10
- apr: upgrade 1.7.2 -> 1.7.4
- apt: Upgrade to v2.6.0
- at-spi2-core: update 2.46.0 -> 2.50.0
- autoconf: Upgrade to 2.72c
- babeltrace2: upgrade 2.0.4 -> 2.0.5
- bind: upgrade 9.18.12 -> 9.18.19
- binutils: Upgrade to 2.41 release
- bluez5: upgrade 5.66 -> 5.69
- boost: upgrade 1.81.0 -> 1.83.0
- btrfs-tools: upgrade 6.1.3 -> 6.5.1
- busybox: 1.36.0 -> 1.36.1
- ccache: upgrade 4.7.4 -> 4.8.3
- cmake: upgrade to 3.27.5
- connman: update 1.41 -> 1.42
- coreutils: upgrade 9.1 -> 9.4
- cpio: upgrade to 2.14
- cracklib: upgrade 2.9.10 -> 2.9.11
- createrepo-c: update 0.20.1 -> 1.0.0
- cryptodev: update to 1.13 + latest git

- cups: upgrade to 2.4.6
- curl: upgrade 8.0.1 -> 8.4.0
- dbus: upgrade 1.14.6 -> 1.14.10
- debianutils: upgrade 5.8 -> 5.13
- dhcpcd: upgrade to 10.0.2
- diffoscope: upgrade 236 -> 249
- diffutils: update 3.9 -> 3.10
- dmidecode: upgrade to 3.5
- dnf: upgrade 4.14.0 -> 4.17.0
- dos2unix: upgrade 7.4.4 -> 7.5.1
- dpkg: upgrade to v1.22.0
- efivar: Upgrade to tip of trunk
- elfutils: upgrade 0.188 -> 0.189
- ell: upgrade 0.56 -> 0.58
- enchant2: upgrade 2.3.4 -> 2.6.1
- epiphany: upgrade 43.1 -> 44.6
- erofs-utils: update 1.5 -> 1.6
- ethtool: upgrade 6.2 -> 6.5
- eudev: Upgrade 3.2.11 -> 3.2.12
- ffmpeg: update 5.1.2 -> 6.0
- file: upgrade 5.44 -> 5.45
- flac: Upgrade 1.4.2 -> 1.4.3
- font-util: upgrade 1.4.0 -> 1.4.1
- freetype: upgrade 2.13.0 -> 2.13.2
- fribidi: upgrade 1.0.12 -> 1.0.13
- gawk: upgrade 5.2.1 -> 5.2.2
- gcc: upgrade to 13.2
- gcompat: Upgrade to 1.1.0
- gcr: update 4.0.0 -> 4.1.0
- gdb: upgrade 13.1 -> 13.2
- gettext: upgrade 0.21.1 -> 0.22
- ghostscript: upgrade to 10.02.0

- git: upgrade to 2.42.0
- glib-2.0: upgrade 2.74.6 -> 2.78.0
- glibc: upgrade to 2.38 + stable updates
- glib-networking: upgrade 2.74.0 -> 2.76.1
- glslang: upgrade to 1.3.243
- gmp: upgrade 6.2.1 -> 6.3.0
- gnu-efi: upgrade 3.0.15 -> 3.0.17
- gnupg: upgrade 2.4.0 -> 2.4.3
- gnutls: update 3.8.0 -> 3.8.1
- gobject-introspection: upgrade 1.74.0 -> 1.78.1
- go-helloworld: Upgrade to tip of trunk
- go: update 1.20.1 -> 1.20.10
- gpgme: update 1.18.0 -> 1.22.0
- grep: upgrade 3.10 -> 3.11
- groff: update 1.22.4 -> 1.23.0
- gsettings-desktop-schemas: upgrade 43.0 -> 44.0
- gstreamer1.0: upgrade 1.22.0 -> 1.22.5
- gstreamer: upgrade 1.22.5 -> 1.22.6
- gtk+3: upgrade 3.24.36 -> 3.24.38
- gtk4: update 4.10.0 -> 4.12.3
- gzip: update 1.12 -> 1.13
- harfbuzz: upgrade 7.1.0 -> 8.2.1
- icu: upgrade 72-1 -> 73-2
- igt-gpu-tools: update 1.27.1 -> 1.28
- iproute2: upgrade 6.2.0 -> 6.5.0
- iso-codes: upgrade 4.13.0 -> 4.15.0
- jquery: upgrade 3.6.3 -> 3.7.1
- json-c: upgrade 0.16 -> 0.17
- kbd: upgrade 2.5.1 -> 2.6.3
- kea: upgrade to v2.4.0
- kexec-tools: upgrade 2.0.26 -> 2.0.27
- kmscube: upgrade to latest revision



- less: update 608 -> 643
- libadwaita: upgrade 1.3.3 -> 1.4.0
- libarchive: upgrade 3.6.2 -> 3.7.2
- libassuan: upgrade 2.5.5 -> 2.5.6
- libatomic-ops: update 7.6.14 -> 7.8.0
- libcap: upgrade 2.67 -> 2.69
- libccgroup: update 3.0.0 -> 3.1.0
- libconvert-asn1-perl: upgrade 0.33 -> 0.34
- libdnf: update 0.70.1 -> 0.70.1
- libdrm: upgrade 2.4.115 -> 2.4.116
- libedit: upgrade 20221030-3.1 -> 20230828-3.1
- libevdev: upgrade 1.13.0 -> 1.13.1
- libgcrypt: update 1.10.1 -> 1.10.2
- libgit2: upgrade 1.6.3 -> 1.7.1
- libglu: update 9.0.2 -> 9.0.3
- libgpg-error: update 1.46 -> 1.47
- libgudev: upgrade 237 -> 238
- libhandy: upgrade 1.8.1 -> 1.8.2
- libinput: upgrade to 1.24.0
- libjpeg-turbo: upgrade to 3.0.0
- libksba: upgrade 1.6.3 -> 1.6.4
- libmd: upgrade 1.0.4 -> 1.1.0
- libmicrohttpd: upgrade 0.9.76 -> 0.9.77
- libmodule-build-perl: upgrade 0.4232 -> 0.4234
- libmodulemd: upgrade 2.14.0 -> 2.15.0
- libnl: upgrade 3.7.0 -> 3.8.0
- libnss-nis: upgrade 3.1 -> 3.2
- libpam: update 1.5.2 -> 1.5.3
- libpcap: upgrade 1.10.3 -> 1.10.4
- libpng: upgrade 1.6.39 -> 1.6.40
- libportal: upgrade 0.6 -> 0.7.1
- libproxy: update 0.4.18 -> 0.5.3

- libpthread-stubs: update 0.4 -> 0.5
- librepo: upgrade 1.15.1 -> 1.16.0
- librsvf: update 2.54.5 -> 2.56.0
- librsvg: update 2.56.0 -> 2.56.3
- libsdl2: upgrade 2.26.3 -> 2.28.3
- libsecret: upgrade 0.20.5 -> 0.21.1
- libsndfile1: upgrade 1.2.0 -> 1.2.2
- libsolv: upgrade 0.7.23 -> 0.7.25
- libsoup: upgrade 3.2.2 -> 3.4.2
- libssh2: update 1.10.0 -> 1.11.0
- libtraceevent: upgrade 1.7.2 -> 1.7.3
- libubootenv: upgrade 0.3.3 -> 0.3.4
- liburi-perl: update 5.17 -> 5.21
- libuv: upgrade 1.44.2 -> 1.46.0
- libva: update 2.16 -> 2.19.0
- libva-utils: update 2.19.0 -> 2.20.0
- libwebp: upgrade 1.3.0 -> 1.3.2
- libx11: upgrade 1.8.4 -> 1.8.7
- libxcb: upgrade 1.15 -> 1.16
- libxcrypt: upgrade 4.4.33 -> 4.4.36
- libxfixes: Upgrade to v6.0.1
- libxft: upgrade 2.3.7 -> 2.3.8
- libxi: upgrade to v1.8.1
- libxml2: upgrade 2.10.3 -> 2.11.5
- libxpm: upgrade 3.5.15 -> 3.5.17
- libxslt: upgrade 1.1.37 -> 1.1.38
- libxt: Upgrade to v1.3.0
- lighttpd: upgrade 1.4.69 -> 1.4.71
- linux-firmware: upgrade 20230210 -> 20230804
- linux-libc-headers: uprev to v6.5
- linux-yocto/6.1: update to v6.1.57
- linux-yocto-dev: update to v6.6-rcX

- linux-yocto: introduce 6.5 reference kernel recipes
- llvm: Upgrade to 17.0.2
- ltp: upgrade 20230127 -> 20230516
- ltng-modules: Upgrade 2.13.9 -> 2.13.10
- ltng-tools: Upgrade 2.13.9 -> 2.13.11
- ltng-ust: upgrade 2.13.5 -> 2.13.6
- lua: update 5.4.4 -> 5.4.6
- man-pages: upgrade 6.03 -> 6.05.01
- mc: upgrade 4.8.29 -> 4.8.30
- mesa: upgrade 23.0.0 -> 23.2.1
- meson: upgrade 1.0.1 -> 1.2.2
- mmc-utils: upgrade to latest revision
- mobile-broadband-provider-info: upgrade 20221107 -> 20230416
- mpfr: upgrade 4.2.0 -> 4.2.1
- mpg123: upgrade 1.31.2 -> 1.31.3
- msmtmp: upgrade 1.8.23 -> 1.8.24
- mtd-utils: upgrade 2.1.5 -> 2.1.6
- mtools: upgrade 4.0.42 -> 4.0.43
- musl: update to latest master
- neard: upgrade 0.18 -> 0.19
- nettle: upgrade 3.8.1 -> 3.9.1
- nfs-utils: upgrade 2.6.2 -> 2.6.3
- nghttp2: upgrade 1.52.0 -> 1.57.0
- ofono: upgrade 2.0 -> 2.1
- openssh: upgrade to 9.5p1
- openssl: upgrade 3.1.0 -> 3.1.3
- opkg: upgrade 0.6.1 -> 0.6.2
- opkg-utils: upgrade 0.5.0 -> 0.6.2
- orc: upgrade 0.4.33 -> 0.4.34
- ovmf: update 202211 -> 202305
- ovmf: update edk2-stable202305 -> edk2-stable202308
- p11-kit: upgrade 0.24.1 -> 0.25.0

- pango: upgrade 1.50.13 -> 1.51.0
- parted: upgrade 3.5 -> 3.6
- patchelf: Upgrade 0.17.2 -> 0.18.0
- pciutils: upgrade 3.9.0 -> 3.10.0
- perlcross: update 1.4 -> 1.5
- perl: update 5.36.0 -> 5.38.0
- piglit: upgrade to latest revision
- pigz: upgrade 2.7 -> 2.8
- pkgconf: upgrade 1.9.4 -> 2.0.3
- ppp: upgrade 2.4.9 -> 2.5.0
- procs: update 4.0.3 -> 4.0.4
- puzzles: upgrade to latest revision
- python3-attrs: upgrade 22.2.0 -> 23.1.0
- python3-build: upgrade to 1.0.3
- python3-certifi: upgrade 2022.12.7 -> 2023.7.22
- python3-chardet: upgrade 5.1.0 -> 5.2.0
- python3-cryptography{-vectors}: upgrade 39.0.2 -> 41.0.4
- python3-cython: upgrade 0.29.33 -> 0.29.36
- python3-dbusmock: upgrade 0.28.7 -> 0.29.1
- python3-docutils: upgrade 0.19 -> 0.20.1
- python3-dtc: upgrade 1.6.1 -> 1.7.0
- python3-dtschema: upgrade 2023.1 -> 2023.7
- python3-editables: upgrade 0.3 -> 0.5
- python3-flit-core: upgrade 3.8.0 -> 3.9.0
- python3-git: upgrade 3.1.31 -> 3.1.36
- python3-hatch-fancy-pypi-readme: upgrade 22.8.0 -> 23.1.0
- python3-hatchling: upgrade 1.13.0 -> 1.18.0
- python3-hypothesis: upgrade 6.68.2 -> 6.86.2
- python3-importlib-metadata: upgrade 6.0.0 -> 6.8.0
- python3-installer: upgrade 0.6.0 -> 0.7.0
- python3-iso8601: upgrade 1.1.0 -> 2.0.0
- python3-jsonpointer: upgrade to 2.4

- python3-libarchive-c: upgrade 4.0 -> 5.0
- python3-lxml: upgrade 4.9.2 -> 4.9.3
- python3-markdown: upgrade 3.4.1 -> 3.4.4
- python3-markupsafe: upgrade 2.1.2 -> 2.1.3
- python3-more-itertools: upgrade 9.1.0 -> 10.1.0
- python3-numpy: upgrade 1.24.2 -> 1.26.0
- python3-packaging: upgrade 23.0 -> 23.1
- python3-pathspect: upgrade 0.11.0 -> 0.11.2
- python3-pip: upgrade 23.0.1 -> 23.2.1
- python3-pluggy: upgrade 1.0.0 -> 1.3.0
- python3-poetry-core: upgrade 1.5.2 -> 1.7.0
- python3-psutil: upgrade 5.9.4 -> 5.9.5
- python3-pyasn1: upgrade 0.4.8 -> 0.5.0
- python3-pycairo: upgrade 1.23.0 -> 1.24.0
- python3-pycryptodome: upgrade 3.17 -> 3.19.0
- python3-pycryptodomex: upgrade 3.17 -> 3.19.0
- python3-pyelftools: upgrade 0.29 -> 0.30
- python3-pygments: upgrade 2.14.0 -> 2.16.1
- python3-pygobject: upgrade 3.42.2 -> 3.46.0
- python3-pyopenssl: upgrade 23.0.0 -> 23.2.0
- python3-pyparsing: upgrade 3.0.9 -> 3.1.1
- python3-pytest-subtests: upgrade 0.10.0 -> 0.11.0
- python3-pytest: upgrade 7.2.2 -> 7.4.2
- python3-pytz: upgrade 2022.7.1 -> 2023.3
- python3-pyyaml: upgrade 6.0 -> 6.0.1
- python3-requests: Upgrade to 2.31.0
- python3-ruamel-yaml: upgrade 0.17.21 -> 0.17.32
- python3-setuptools-rust: upgrade 1.5.2 -> 1.7.0
- python3-setuptools: upgrade 67.6.0 -> 68.2.2
- python3-smmap: upgrade 5.0.0 -> 6.0.0
- python3-sphinx-rtd-theme: upgrade 1.2.0 -> 1.3.0
- python3-sphinx: upgrade 6.1.3 -> 7.2.6

- python3-trove-classifiers: upgrade 2023.4.29 -> 2023.9.19
- python3-typing-extensions: upgrade 4.5.0 -> 4.8.0
- python3: upgrade 3.11.2 -> 3.11.5
- python3-urllib3: upgrade 1.26.15 -> 2.0.6
- python3-webcolors: upgrade 1.12 -> 1.13
- python3-wheel: upgrade 0.40.0 -> 0.41.2
- python3-zipp: upgrade 3.15.0 -> 3.17.0
- qemu: Upgrade 7.2.0 -> 8.1.0
- re2c: upgrade 3.0 -> 3.1
- repo: upgrade 2.32 -> 2.36.1
- rpcsvc-proto: Upgrade to 1.4.4
- rpm2cpio.sh: update to the last 4.x version
- rpm: update 4.18.0 -> 4.18.1
- ruby: upgrade 3.2.1 -> 3.2.2
- rust: Upgrade 1.68.1 -> 1.70.0
- screen: update 4.9.0 -> 4.9.1
- seatd: upgrade 0.7.0 -> 0.8.0
- serf: upgrade 1.3.9 -> 1.3.10
- shaderc: upgrade 2023.2 -> 2023.6
- spirv-headers: upgrade 1.3.239.0 -> 1.3.243.0
- spirv-tools: upgrade 1.3.239.0 -> 1.3.243.0
- sqlite3: upgrade 3.41.0 -> 3.43.1
- squashfs-tools: upgrade 4.5.1 -> 4.6.1
- sstatesig: Update to match bitbake changes to runtaskdeps
- strace: upgrade 6.2 -> 6.5
- stress-ng: upgrade 0.15.06 -> 0.16.05
- sudo: update 1.9.13p3 -> 1.9.14p3
- sysfsutils: update 2.1.0 -> 2.1.1
- sysklogd: upgrade 2.4.4 -> 2.5.2
- sysstat: update 12.6.2 -> 12.7.4
- systemd: upgrade 253.1 -> 254.4
- systemtap: upgrade 4.8 -> 4.9

- taglib: upgrade 1.13 -> 1.13.1
- tar: upgrade 1.34 -> 1.35
- tcf-agent: Update to 1.8.0 release
- texinfo: upgrade 7.0.2 -> 7.0.3
- tiff: upgrade to 4.6.0
- u-boot: Upgrade to 2023.10
- util-linux: upgrade 2.38.1 -> 2.39.2
- vala: upgrade 0.56.4 -> 0.56.13
- valgrind: update 3.20.0 -> 3.21.0
- vim: upgrade 9.0.1429 -> 9.0.2048
- vte: upgrade 0.72.0 -> 0.72.2
- vulkan-headers: upgrade to 1.3.243
- vulkan-loader: upgrade to 1.3.243
- vulkan-samples: update to latest SHA
- vulkan-tools: upgrade to 1.3.243
- vulkan: upgrade 1.3.243.0 -> 1.3.261.1
- waffle: upgrade 1.7.0 -> 1.7.2
- wayland-protocols: upgrade 1.31 -> 1.32
- wayland: upgrade 1.21.0 -> 1.22.0
- wayland-utils: upgrade 1.1.0 -> 1.2.0
- webkitgtk: update 2.38.5 -> 2.40.5
- weston: update 11.0.1 -> 12.0.2
- wget: upgrade 1.21.3 -> 1.21.4
- wireless-regdb: upgrade 2023.02.13 -> 2023.09.01
- wpebackend-fdo: upgrade 1.14.0 -> 1.14.2
- xcb-proto: upgrade 1.15.2 -> 1.16.0
- xdpinfo: upgrade 1.3.3 -> 1.3.4
- xeyes: upgrade 1.2.0 -> 1.3.0
- xf86-input-libinput: upgrade 1.2.1 -> 1.4.0
- xf86-input-mouse: upgrade 1.9.4 -> 1.9.5
- xinput: upgrade to v1.6.4
- xkeyboard-config: upgrade 2.38 -> 2.39

- xorgproto: upgrade 2022.2 -> 2023.2
- xserver-xorg: upgrade 21.1.7 -> 21.1.8
- xtrans: update 1.4.0 -> 1.5.0
- xwayland: upgrade 22.1.8 -> 23.2.1
- xwininfo: upgrade to v1.1.6
- xxhash: upgrade 0.8.1 -> 0.8.2
- xz: upgrade 5.4.2 -> 5.4.4
- zlib: upgrade 1.2.13 -> 1.3
- zstd: upgrade 1.5.4 -> 1.5.5

### **Contributors to 4.3**

Thanks to the following people who contributed to this release:

- Adrian Freihofer
- Alassane Yattara
- Alberto Pianon
- Alberto Planas
- Alejandro Hernandez Samaniego
- Alexander Kanavin
- Alexandre Belloni
- Alexis Lothoré
- Alex Kiernan
- Andreas Cord-Landwehr
- André Draszik
- Andrej Valek
- Andrew Jeffery
- Andrey Zhizhikin
- Angelo Ribeiro
- Antoine Lubineau
- Antonin Godard
- Anuj Mittal
- Archana Polampalli
- Armin Kuster
- Arne Schwerdt



- Arno Baumfalk
- Arslan Ahmad
- Bartosz Golaszewski
- BELHADJ SALEM Talel
- BELOUARGA Mohamed
- Benjamin Bara
- Benjamin Bouvier
- Bergin, Peter
- Bruce Ashfield
- Changhyeok Bae
- Changqing Li
- Charles-Antoine Couret
- Charlie Wu
- Chen Qi
- Chi Xu
- Chris Laplante
- Christopher Larson
- Daniel Ammann
- Daniel McGregor
- Daniel Semkowicz
- David Reyna
- Deepthi Hemraj
- Denis OSTERLAND-HEIM
- Denys Dmytriyenko
- Derek Straka
- Dit Kozmaj
- Dmitry Baryshkov
- Ed Berozet
- Eero Aaltonen
- Eilís 'pidge' Ní Fhlannagáin
- Emil Ekmečić
- Emil Kronborg Andersen

- Enrico Jörns
- Enrico Scholz
- Etienne Cordonnier
- Fabien Mahot
- Fabio Estevam
- Fahad Arslan
- Frank WOLFF
- Frederic Martinsons
- Frieder Paape
- Frieder Schrempf
- Geoff Parker
- Hannu Lounento
- Ian Ray
- Insu Park
- Jaeyoon Jung
- Jamin Lin
- Jan Garcia
- Jan Vermaete
- Jasper Orschulko
- Jean-Marie Lemetayer
- Jérémy Rosen
- Jermain Horsman
- Jialing Zhang
- Joel Stanley
- Joe Slater
- Johannes Schrimpf
- Jon Mason
- Jörg Sommer
- Jose Quaresma
- Joshua Watt
- Julien Stephan
- Kai Kang

- Khem Raj
- Kyle Russell
- Lee Chee Yang
- Lei Maohui
- Leon Anavi
- Lorenzo Arena
- Louis Rannou
- Luan Rafael Carneiro
- Luca Boccassi
- Luca Ceresoli
- Marc Ferland
- Marcus Flyckt
- Marek Vasut
- Mark Asselstine
- Mark Hatle
- Markus Niebel
- Markus Volk
- Marlon Rodriguez Garcia
- Marta Rybczynska
- Martijn de Gouw
- Martin Jansa
- Martin Siegumfeldt
- Matthias Schnelte
- Mauro Queiros
- Max Krummenacher
- Michael Halstead
- Michael Opdenacker
- Mickael RAMILISON
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Narpat Mali

- Natasha Bailey
- Nikhil R
- Ninad Palsule
- Ola x Nilsson
- Oleksandr Hnatiuk
- Otavio Salvador
- Ovidiu Panait
- Pascal Bach
- Patrick Williams
- Paul Eggleton
- Paul Gortmaker
- Paulo Neves
- Pavel Zhukov
- Pawan Badganchi
- Peter Bergin
- Peter Hoyes
- Peter Kjellerstedt
- Peter Marko
- Peter Suti
- Petr Gotthard
- Petr Kubizňák
- Piotr Łobacz
- Poonam Jadhav
- Qiu Tingting
- Quentin Schulz
- Randolph Sapp
- Randy MacLeod
- Ranjitsinh Rathod
- Rasmus Villemoes
- Remi Peuvergne
- Richard Purdie
- Riyaz Khan

- Robert Joslyn
- Robert P. J. Day
- Robert Yang
- Roland Hieber
- Ross Burton
- Ryan Eatmon
- Sakib Sajal
- Samantha Jalabert
- Sanjay Chitroda
- Sean Nyekjaer
- Sergei Zhmylev
- Siddharth Doshi
- Soumya Sambu
- Staffan Rydén
- Stefano Babic
- Stefan Tauner
- Stéphane Veyret
- Stephan Wurm
- Sudip Mukherjee
- Sundeep KOKKONDA
- Svend Meyland Nicolaisen
- Tan Wen Yan
- Thomas Roos
- Tim Orling
- Tom Hochstein
- Tom Isaacson
- Trevor Gamblin
- Ulrich Ölmann
- Victor Kamensky
- Vincent Davis Jr
- Virendra Thakur
- Wang Mingyu

- Xiangyu Chen
- Yang Xu
- Yash Shinde
- Yi Zhao
- Yoann Congal
- Yogita Urade
- Yuta Hayama
- Zang Ruochen
- Zhixiong Chi

## Repositories / Downloads for Yocto-4.3

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `nanbield`
- Tag: `yocto-4.3`
- Git Revision: `15b576c4101231d248fda7ae0824e1780e1a8901`
- Release Artefact: `poky-15b576c4101231d248fda7ae0824e1780e1a8901`
- sha: `6b0ef7914d15db057f3efdf091b169a7361c74aac0abcfa717ef55d1a0adf74c`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3/poky-15b576c4101231d248fda7ae0824e1780e1a8901.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3/poky-15b576c4101231d248fda7ae0824e1780e1a8901.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `nanbield`
- Tag: `yocto-4.3`
- Git Revision: `4c261f8cbdf0c7196a74daad041d04eb093015f3`
- Release Artefact: `oecore-4c261f8cbdf0c7196a74daad041d04eb093015f3`
- sha: `c9e6ac75d7848ce8844cb29c98659dd8f83b3de13b916124dff76abe034e6a5c`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3/oecore-4c261f8cbdf0c7196a74daad041d04eb093015f3.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3/oecore-4c261f8cbdf0c7196a74daad041d04eb093015f3.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `nanbield`

- Tag: `yocto-4.3`
- Git Revision: `65ef95a74f6ae815f63f636ed53e140a26a014ce`
- Release Artefact: `meta-mingw-65ef95a74f6ae815f63f636ed53e140a26a014ce`
- sha: `fb2bf806941a00a1be6349c074379b63a76490bcf0f3b740d96d1aecefa12286`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3/meta-mingw-65ef95a74f6ae815f63f636ed53e140a26a014ce.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3/meta-mingw-65ef95a74f6ae815f63f636ed53e140a26a014ce.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.6`
- Tag: `yocto-4.3`
- Git Revision: `5419a8473d6d4cd1d01537de68ad8d72cf5be0b2`
- Release Artefact: `bitbake-5419a8473d6d4cd1d01537de68ad8d72cf5be0b2`
- sha: `e5dab4b3345d91307860803e2ad73b2fcffa9d17dd3fde0e013ca0e0bea0d05ca`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3/bitbake-5419a8473d6d4cd1d01537de68ad8d72cf5be0b2.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3/bitbake-5419a8473d6d4cd1d01537de68ad8d72cf5be0b2.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `nanbield`
- Tag: `yocto-4.3`
- Git Revision: `ceb1812e63b9fac062f886c2a1dde23137c0e1ed`

### 17.8.3 Release notes for Yocto-4.3.1 (Nanbield)

#### Security Fixes in Yocto-4.3.1

- `libsndfile1`: Fix CVE-2022-33065
- `libxml2`: Ignore CVE-2023-45322
- `linux-yocto/6.1`: Ignore CVE-2020-27418, CVE-2023-31085, CVE-2023-34324, CVE-2023-39189, CVE-2023-39192, CVE-2023-39193, CVE-2023-39194, CVE-2023-4244, CVE-2023-42754, CVE-2023-42756, CVE-2023-44466, CVE-2023-4563, CVE-2023-45862, CVE-2023-45863, CVE-2023-45871, CVE-2023-45898, CVE-2023-4732, CVE-2023-5158, CVE-2023-5197 and CVE-2023-5345
- `linux-yocto/6.5`: Ignore CVE-2020-27418, CVE-2023-1193, CVE-2023-39191, CVE-2023-39194, CVE-2023-40791, CVE-2023-44466, CVE-2023-45862, CVE-2023-45863, CVE-2023-4610 and CVE-2023-4732
- `openssl`: Fix CVE-2023-5363

- pixman: Ignore [CVE-2023-37769](#)
- vim: Fix [CVE-2023-46246](#)
- zlib: Ignore [CVE-2023-45853](#)

### Fixes in Yocto-4.3.1

- baremetal-helloworld: Pull in fix for race condition on x86-64
- base: Ensure recipes using mercurial-native have certificates
- bb-matrix-plot.sh: Show underscores correctly in labels
- bin\_package.bbclass: revert "Inhibit the default dependencies"
- bitbake: SECURITY.md: add file
- brief-yoctoprojectqs: use new CDN mirror for sstate
- bsp-guide: bsp.rst: update beaglebone example
- bsp-guide: bsp: skip Intel machines no longer supported in Poky
- build-appliance-image: Update to nanbield head revision
- contributor-guide: add patchtest section
- contributor-guide: clarify patchtest usage
- cve-check: don't warn if a patch is remote
- cve-check: slightly more verbose warning when adding the same package twice
- cve-check: sort the package list in the JSON report
- dev-manual: add security team processes
- dev-manual: extend the description of CVE patch preparation
- dev-manual: layers: Add notes about layer.conf
- dev-manual: new-recipe.rst: add missing parenthesis to "Patching Code" section
- dev-manual: start.rst: remove obsolete reference
- dev-manual: wic: update "wic list images" output
- docs: add support for nanbield (4.3) release
- documentation.conf: drop SERIAL\_CONSOLES\_CHECK
- ell: Upgrade to 0.59
- glib-2.0: Remove unnecessary assignement
- goarch: Move Go architecture mapping to a library
- kernel-arch: drop CCACHE from *KERNEL\_STRIP* definition
- kernel.bbclass: Use strip utility used for kernel build in do\_package
- layer.conf: Switch layer to nanbield series only



- libSDL2: upgrade to 2.28.4
- linux-yocto: make sure the pahole-native available before do\_kernel\_configme
- LLVM: Upgrade to 17.0.3
- machine: drop obsolete SERIAL\_CONSOLES\_CHECK
- manuals: correct "yocto-linux" by "linux-yocto"
- manuals: improve description of *CVE\_STATUS* and *CVE\_STATUS\_GROUPS*
- manuals: Remove references to apm in *MACHINE\_FEATURES*
- manuals: update linux-yocto append examples
- manuals: update list of supported machines
- migration-4.3: additional migration items
- migration-4.3: adjustments to existing text
- migration-4.3: remove some unnecessary items
- migration-guides: QEMU\_USE\_SLIRP variable removed
- migration-guides: add BitBake changes
- migration-guides: add debian 12 to newly supported distros
- migration-guides: add kernel notes
- migration-guides: add testing notes
- migration-guides: add utility notes
- migration-guides: edgerouter machine removed
- migration-guides: enabling *SPDX* only for Poky, not a global default
- migration-guides: fix empty sections
- migration-guides: further updates for 4.3
- migration-guides: further updates for release 4.3
- migration-guides: git recipes reword
- migration-guides: mention CDN
- migration-guides: mention LLVM 17
- migration-guides: mention runqemu change in serial port management
- migration-guides: packaging changes
- migration-guides: remove SERIAL\_CONSOLES\_CHECK
- migration-guides: remove non-notable change
- migration-guides: updates for 4.3
- oeqa/selftest/debuginfod: improve selftest

- oeqa/selftest/devtool: abort if a local workspace already exist
- oeqa/ssh: Handle SSHCall timeout error code
- openssl: Upgrade to 3.1.4
- overview-manual: concepts: Add Bitbake Tasks Map
- patchtest-send-results: add In-Reply-To
- patchtest-send-results: check max line length, simplify responses
- patchtest-send-results: fix sender parsing
- patchtest-send-results: improve subject line
- patchtest-send-results: send results to submitter
- patchtest/selftest: add XSKIP, update test files
- patchtest: disable merge test
- patchtest: fix lic\_files\_chksum test regex
- patchtest: make pylint tests compatible with 3.x
- patchtest: reduce checksum test output length
- patchtest: remove test for CVE tag in mbox
- patchtest: remove unused imports
- patchtest: rework license checksum tests
- patchtest: shorten test result outputs
- patchtest: simplify test directory structure
- patchtest: skip merge test if not targeting master
- patchtest: test regardless of mergeability
- perl: fix intermittent test failure
- poky.conf: bump version for 4.3.1 release
- profile-manual: aesthetic cleanups
- ref-manual: Add documentation for the unimplemented-ptest QA warning
- ref-manual: Fix *PACKAGECONFIG* term and add an example
- ref-manual: Warn about *COMPATIBLE\_MACHINE* skipping native recipes
- ref-manual: add systemd-resolved to distro features
- ref-manual: classes: explain cml1 class name
- ref-manual: document *KERNEL\_LOCALVERSION*
- ref-manual: document *KERNEL\_STRIP*
- ref-manual: document *MESON\_TARGET*

- ref-manual: document cargo\_c class
- ref-manual: remove semicolons from \*PROCESS\_COMMAND variables
- ref-manual: update *SDK\_NAME* variable documentation
- ref-manual: variables: add *RECIPE\_MAINTAINER*
- ref-manual: variables: add *RECIPE\_SYSROOT* and *RECIPE\_SYSROOT\_NATIVE*
- ref-manual: variables: add *TOOLCHAIN\_OPTIONS* variable
- ref-manual: variables: add example for *SYSROOT\_DIRS* variable
- ref-manual: variables: document *OEQA\_REPRODUCIBLE\_TEST\_PACKAGE*
- ref-manual: variables: mention new CDN for *SSTATE\_MIRRORS*
- ref-manual: variables: provide no-match example for *COMPATIBLE\_MACHINE*
- ref-manual: variables: remove SERIAL\_CONSOLES\_CHECK
- release-notes-4.3: add CVEs, recipe upgrades, license changes, contributors
- release-notes-4.3: add Repositories / Downloads section
- release-notes-4.3: feature additions
- release-notes-4.3: fix some typos
- release-notes-4.3: move new classes to Rust section
- release-notes-4.3: remove the Distribution section
- release-notes-4.3: tweaks to existing text
- sdk-manual: appendix-obtain: improve and update descriptions
- test-manual: reproducible-builds: stop mentioning LTO bug
- vim: Improve locale handling
- vim: Upgrade to 9.0.2068
- vim: use upstream generated .po files

### Known Issues in Yocto-4.3.1

- N/A

### Contributors to Yocto-4.3.1

- Alejandro Hernandez Samaniego
- Alex Stewart
- Archana Polampalli
- Arne Schwerdt
- BELHADJ SALEM Talel
- Dmitry Baryshkov

- Eero Aaltonen
- Joshua Watt
- Julien Stephan
- Jérémy Rosen
- Khem Raj
- Lee Chee Yang
- Marta Rybczynska
- Max Krummenacher
- Michael Halstead
- Michael Opdenacker
- Paul Eggleton
- Peter Kjellerstedt
- Peter Marko
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Ross Burton
- Rouven Czerwinski
- Steve Sakoman
- Trevor Gamblin
- Wang Mingyu
- William Lyu
- Xiangyu Chen
- luca fancellu

## Repositories / Downloads for Yocto-4.3.1

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `nanbield`
- Tag: `yocto-4.3.1`
- Git Revision: `bf9f2f6f60387b3a7cd570919cef6c4570edcb82`
- Release Artefact: `poky-bf9f2f6f60387b3a7cd570919cef6c4570edcb82`
- sha: `9b4351159d728fec2b63a50f1ac15edc412e2d726e9180a40afc06051fadb922`

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.1/poky-bf9f2f6f60387b3a7cd570919cef6c4570edcb82.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.1/poky-bf9f2f6f60387b3a7cd570919cef6c4570edcb82.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: nanbield
- Tag: yocto-4.3.1
- Git Revision: cce77e8e79c860f4ef0ac4a86b9375bf87507360
- Release Artefact: oecore-cce77e8e79c860f4ef0ac4a86b9375bf87507360
- sha: e6cde08e7c549f57a67d833a36cdb942648fba81558dc8b0e65332d2a2c023cc
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.1/oecore-cce77e8e79c860f4ef0ac4a86b9375bf87507360.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.1/oecore-cce77e8e79c860f4ef0ac4a86b9375bf87507360.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: nanbield
- Tag: yocto-4.3.1
- Git Revision: 49617a253e09baabbf0355bc736122e9549c8ab2
- Release Artefact: meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2
- sha: 2225115b73589cdbf1e491115221035c6a61679a92a93b2a3cf761ff87bf4ecc
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.1/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.1/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.6
- Tag: yocto-4.3.1
- Git Revision: 936fcec41efacc4ce988c81882a9ae6403702bea
- Release Artefact: bitbake-936fcec41efacc4ce988c81882a9ae6403702bea
- sha: efbdd5fe7f29227a3fd26d6a08a368bf8215083a588b4d23f3adf35044897520
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.1/bitbake-936fcec41efacc4ce988c81882a9ae6403702bea.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.1/bitbake-936fcec41efacc4ce988c81882a9ae6403702bea.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>

- Branch: `nanbield`
- Tag: `yocto-4.3.1`
- Git Revision: `6b98a6164263298648e89b5a5ae1260a58f1bb35`

## 17.8.4 Release notes for Yocto-4.3.2 (Nanbield)

### Security Fixes in Yocto-4.3.2

- `avahi`: Fix CVE-2023-1981, CVE-2023-38469, CVE-2023-38470, CVE-2023-38471, CVE-2023-38472 and CVE-2023-38473
- `curl`: Fix CVE-2023-46218
- `ghostscript`: Fix CVE-2023-46751
- `grub`: fix CVE-2023-4692 and CVE-2023-4693
- `gststreamer1.0`: Fix CVE-2023-44446
- `linux-yocto/6.1`: Ignore CVE-2023-39197, CVE-2023-39198, CVE-2023-5090, CVE-2023-5633, CVE-2023-6111, CVE-2023-6121 and CVE-2023-6176
- `linux-yocto/6.5`: Ignore CVE-2022-44034, CVE-2023-39197, CVE-2023-39198, CVE-2023-5972, CVE-2023-6039, CVE-2023-6111 and CVE-2023-6176
- `perl`: fix CVE-2023-47100
- `python3-urllib3`: Fix CVE-2023-45803
- `rust`: Fix CVE-2023-40030
- `vim`: Fix CVE-2023-48231, CVE-2023-48232, CVE-2023-48233, CVE-2023-48234, CVE-2023-48235, CVE-2023-48236 and CVE-2023-48237
- `xserver-xorg`: Fix CVE-2023-5367 and CVE-2023-5380
- `xwayland`: Fix CVE-2023-5367

### Fixes in Yocto-4.3.2

- `base-passwd`: Upgrade to 3.6.2
- `bind`: Upgrade to 9.18.20
- `binutils`: stable 2.41 branch updates
- `bitbake`: command: Make `parseRecipeFile()` handle virtual recipes correctly
- `bitbake`: lib/bb: Add workaround for libgcc issues with python 3.8 and 3.9
- `bitbake`: toastergui: verify that an existing layer path is given
- `bluez5`: fix connection for ps5/dualshock controllers
- `build-appliance-image`: Update to nanbield head revision
- `cmake`: Upgrade to 3.27.7
- `contributor-guide`: add License-Update tag

- contributor-guide: fix command option
- cups: Add root,sys,wheel to system groups
- cve-update-nvd2-native: faster requests with API keys
- cve-update-nvd2-native: increase the delay between subsequent request failures
- cve-update-nvd2-native: make number of fetch attempts configurable
- cve-update-nvd2-native: remove unused variable CVE\_SOCKET\_TIMEOUT
- dev-manual: Discourage the use of SRC\_URI[md5sum]
- dev-manual: layers: update link to YP Compatible form
- dev-manual: runtime-testing: fix test module name
- devtool: finish/update-recipe: restrict mode srcrev to recipes fetched from SCM
- devtool: fix update-recipe dry-run mode
- ell: Upgrade to 0.60
- enchant2: Upgrade to 2.6.2
- ghostscript: Upgrade to 10.02.1
- glib-2.0: Upgrade to 2.78.1
- glibc: stable 2.38 branch updates
- gstreamer1.0: Upgrade to 1.22.7
- gtk: Add rdepend on printbackend for cups
- harfbuzz: Upgrade to 8.2.2
- json-c: fix icecc compilation
- kern-tools: bump *SRCREV* for queue processing changes
- kern-tools: make lower context patches reproducible
- kern-tools: update *SRCREV* to include SECURITY.md file
- kernel-arch: use ccache only for compiler
- kernel-yocto: improve metadata patching
- lib/oe/buildcfg.py: Include missing import
- lib/oe/buildcfg.py: Remove unused parameter
- lib/oe/patch: ensure os.chdir restoring always happens
- lib/oe/path: Deploy files can start only with a dot
- libgcrypt: Upgrade to 1.10.3
- libjpeg-turbo: Upgrade to 3.0.1
- libnewt: Upgrade to 0.52.24

- libnsl2: Upgrade to 2.0.1
- libsolve: Upgrade to 0.7.26
- libxslt: Upgrade to 1.1.39
- linux-firmware: add audio topology symlink to the X13's audio package
- linux-firmware: add missing dependencies on license packages
- linux-firmware: add new fw file to \${PN}-rtl8821
- linux-firmware: add notice file to sdm845 modem firmware
- linux-firmware: create separate packages
- linux-firmware: package Qualcomm Venus 6.0 firmware
- linux-firmware: package Robotics RB5 sensors DSP firmware
- linux-firmware: package firmware for Qualcomm Adreno a702
- linux-firmware: package firmware for Qualcomm QCM2290 / QRB4210
- linux-firmware: Upgrade to 20231030
- linux-yocto-rt/6.1: update to -rt18
- linux-yocto/6.1: cfg: restore CONFIG\_DEVMEM
- linux-yocto/6.1: drop removed IMA option
- linux-yocto/6.1: Upgrade to v6.1.68
- linux-yocto/6.5: cfg: restore CONFIG\_DEVMEM
- linux-yocto/6.5: cfg: split runtime and symbol debug
- linux-yocto/6.5: drop removed IMA option
- linux-yocto/6.5: fix AB-INT: QEMU kernel panic: No irq handler for vector
- linux-yocto/6.5: Upgrade to v6.5.13
- linux/cve-exclusion6.1: Update to latest kernel point release
- log4cplus: Upgrade to 2.1.1
- lsb-release: use https for [UPSTREAM\\_CHECK\\_URI](#)
- manuals: brief-yoctoprojectqs: align variable order with default local.conf
- manuals: fix URL
- meson: use correct targets for rust binaries
- migration-guide: add release notes for 4.0.14, 4.0.15, 4.2.4, 4.3.1
- migration-guides: release 3.5 is actually 4.0
- migration-guides: reword fix in release-notes-4.3.1
- msmtmp: Upgrade to 1.8.25



- oeqa/selftest/tinfoil: Add tests that parse virtual recipes
- openssl: improve handshake test error reporting
- package\_ipk: Fix Source: field variable dependency
- patchtest: shorten patch signed-off-by test output
- perf: lift *TARGET\_CC\_ARCH* modification out of security\_flags.inc
- perl: Upgrade to 5.38.2
- perlcross: Upgrade to 1.5.2
- poky.conf: bump version for 4.3.2 release
- python3-ptest: skip test\_storlines
- python3-urllib3: Upgrade to 2.0.7
- qemu: Upgrade to 8.1.2
- ref-manual: Fix reference to MIRRORS/PREMIRRORS defaults
- ref-manual: releases.svg: update nanbield release status
- useradd\_base: sed -i destroys symlinks
- rootfs-postcommands: sed -i destroys symlinks
- sstate: Ensure sstate searches update file mtime
- strace: backport fix for so\_peerpidfd-test
- systemd-boot: Fix build issues on armv7a-linux
- systemd-compatible.bb: fix postinstall script
- systemd: fix DynamicUser issue
- systemd: update *LICENSE* statement
- tcl: skip async and event tests in run-ptest
- tcl: skip timing-dependent tests in run-ptest
- test-manual: add links to python unittest
- test-manual: add or improve hyperlinks
- test-manual: explicit or fix file paths
- test-manual: resource updates
- test-manual: text and formatting fixes
- test-manual: use working example
- testimage: Drop target\_dumper and most of monitor\_dumper
- testimage: Exclude wtmp from target-dumper commands
- tzdata: Upgrade to 2023d

- update\_gtk\_icon\_cache: Fix for GTK4-only builds
- useradd\_base: Fix sed command line for passwd-expire
- vim: Upgrade to 9.0.2130
- xserver-xorg: Upgrade to 21.1.9
- xwayland: Upgrade to 23.2.2

### **Known Issues in Yocto-4.3.2**

- N/A

### **Contributors to Yocto-4.3.2**

- Adam Johnston
- Alexander Kanavin
- Anuj Mittal
- Bastian Krause
- Bruce Ashfield
- Chen Qi
- Deepthi Hemraj
- Dhairya Nagodra
- Dmitry Baryshkov
- Fahad Arslan
- Javier Tia
- Jermain Horsman
- Joakim Tjernlund
- Julien Stephan
- Justin Bronder
- Khem Raj
- Lee Chee Yang
- Marco Felsch
- Markus Volk
- Marta Rybczynska
- Massimiliano Minella
- Michael Opdenacker
- Paul Barker
- Peter Kjellerstedt

- Peter Marko
- Randy MacLeod
- Rasmus Villemoes
- Richard Purdie
- Ross Burton
- Shubham Kulkarni
- Simone Weiß
- Steve Sakoman
- Sundeep KOKKONDA
- Tim Orling
- Trevor Gamblin
- Vijay Anusuri
- Viswanath Kraleti
- Vyacheslav Yurkov
- Wang Mingyu
- William Lyu
- Zoltán Böszörményi

## Repositories / Downloads for Yocto-4.3.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `nanbield`
- Tag: `yocto-4.3.2`
- Git Revision: `f768ffb8916feb6542fcbe3e946cbf30e247b151`
- Release Artefact: `poky-f768ffb8916feb6542fcbe3e946cbf30e247b151`
- sha: `21ca1695d70aba9b4bd8626d160111feab76206883cd14fe41eb024692bdfd7b`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.2/poky-f768ffb8916feb6542fcbe3e946cbf30e247b151.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.2/poky-f768ffb8916feb6542fcbe3e946cbf30e247b151.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `nanbield`
- Tag: `yocto-4.3.2`
- Git Revision: `ff595b937d37d2315386aebf315cea719e2362ea`

- Release Artefact: `oecore-ff595b937d37d2315386aebf315cea719e2362ea`
- sha: `a7c6332dc0e09ecc08221e78b11151e8e2a3fd9fa3caad96a4c03b67012bfb97`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.2/oecore-ff595b937d37d2315386aebf315cea719e2362ea.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.2/oecore-ff595b937d37d2315386aebf315cea719e2362ea.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `nanbield`
- Tag: `yocto-4.3.2`
- Git Revision: `49617a253e09baabbf0355bc736122e9549c8ab2`
- Release Artefact: `meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2`
- sha: `2225115b73589cdbf1e491115221035c6a61679a92a93b2a3cf761ff87bf4ecc`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.2/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.2/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.6`
- Tag: `yocto-4.3.2`
- Git Revision: `72bf75f0b2e7f36930185e18a1de8277ce7045d8`
- Release Artefact: `bitbake-72bf75f0b2e7f36930185e18a1de8277ce7045d8`
- sha: `0b6ccd4796ccd211605090348a3d4378358c839ae1bb4c35964d0f36f2663187`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.2/bitbake-72bf75f0b2e7f36930185e18a1de8277ce7045d8.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.2/bitbake-72bf75f0b2e7f36930185e18a1de8277ce7045d8.tar.bz2>

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `nanbield`
- Tag: `yocto-4.3.2`
- Git Revision: `fac88b9e80646a68b31975c915a718a9b6b2b439`

## 17.8.5 Release notes for Yocto-4.3.3 (Nanbield)

### Security Fixes in Yocto-4.3.3

- curl: Fix CVE-2023-46219
- glibc: Ignore fixed CVE-2023-0687 and CVE-2023-5156
- linux-yocto/6.1: Ignore CVE-2022-48619, CVE-2023-4610, CVE-2023-5178, CVE-2023-5972, CVE-2023-6040, CVE-2023-6531, CVE-2023-6546, CVE-2023-6622, CVE-2023-6679, CVE-2023-6817, CVE-2023-6931, CVE-2023-6932, CVE-2023-7192, CVE-2024-0193 and CVE-2024-0443
- linux-yocto/6.1: Fix CVE-2023-1193, CVE-2023-51779, CVE-2023-51780, CVE-2023-51781, CVE-2023-51782 and CVE-2023-6606
- qemu: Fix CVE-2023-3019
- shadow: Fix CVE-2023-4641
- sqlite3: Fix CVE-2024-0232
- sqlite3: drop obsolete CVE ignore CVE-2023-36191
- sudo: Fix CVE-2023-42456 and CVE-2023-42465
- tiff: Fix CVE-2023-6277
- xwayland: Fix CVE-2023-6377 and CVE-2023-6478

### Fixes in Yocto-4.3.3

- aspell: upgrade to 0.60.8.1
- avahi: update URL for new project location
- base-passwd: upgrade to 3.6.3
- bitbake: asynrpc: Add context manager API
- bitbake: toaster/toastergui: Bug-fix verify given layer path only if import/add local layer
- build-appliance-image: Update to nanbield head revision
- classes-global/sstate: Fix variable typo
- cmake: Unset CMAKE\_CXX\_IMPLICIT\_INCLUDE\_DIRECTORIES
- contributor-guide: fix lore URL
- contributor-guide: use "apt" instead of "aptitude"
- create-spdx-2.2: combine spdx can try to write before dir creation
- curl: Disable test 1091 due to intermittent failures
- curl: Disable two intermittently failing tests
- dev-manual: gen-tapdevs need iptables installed
- dev-manual: start.rst: Update use of Download page
- dev-manual: update license manifest path

- devtool: deploy: provide max\_process to strip\_execs
- devtool: modify: Handle recipes with a menuconfig task correctly
- docs: document VSCode extension
- dtc: preserve version also from shallow git clones
- elfutils: Update license information
- glib-2.0: upgrade to 2.78.3
- glibc-y2038-tests: do not run tests using 32 bit time APIs
- go: upgrade to 1.20.12
- grub: fs/fat: Don't error when mtime is 0
- gstreamer1.0: upgrade to 1.22.8
- icon-naming-utils: take tarball from debian
- kea: upgrade to 2.4.1
- lib/prservice: Improve lock handling robustness
- libadwaita: upgrade to 1.4.2
- libatomic-ops: upgrade to 7.8.2
- libva-utils: upgrade to 2.20.1
- linux-firmware: Change bnx2 packaging
- linux-firmware: Create bnx2x subpackage
- linux-firmware: Fix the linux-firmware-bcm4373 *FILES* variable
- linux-firmware: Package iwlwifi .pnvm files
- linux-yocto/6.1: security/cfg: add configs to harden protection
- linux-yocto/6.1: update to v6.1.73
- meta/documentation.conf: fix do\_menuconfig description
- migration-guide: add release notes for 4.0.16
- migration-guide: add release notes for 4.3.2
- ncurses: Fix - tty is hung after reset
- nfs-utils: Update Upstream-Status
- nfs-utils: upgrade to 2.6.4
- oeqa/selftest/prservice: Improve test robustness
- package.py: OEHasPackage: Add *MLPREFIX* to packagename
- poky.conf: bump version for 4.3.3 release
- pseudo: Update to pull in syncfs probe fix

- python3-license-expression: Fix the ptest failure
- qemu.bbclass: fix a python TypeError
- qemu: upgrade to 8.1.4
- ref-manual: Add UBOOT\_BINARY, extend *UBOOT\_CONFIG*
- ref-manual: classes: remove insserv bbclass
- ref-manual: update tested and supported distros
- release-notes-4.3: fix spacing
- rootfs.py: check depmodwrapper execution result
- rpcbind: Specify state directory under /run
- scripts/runqemu: fix regex escape sequences
- sqlite3: upgrade to 3.43.2
- sstate: Fix dir ownership issues in *SSTATE\_DIR*
- sudo: upgrade to 1.9.15p5
- tcl: Fix prepending to run-ptest script
- uninative-tarball.xz - reproducibility fix
- xwayland: upgrade to 23.2.3
- zstd: fix *LICENSE* statement

### Known Issues in Yocto-4.3.3

- N/A

### Contributors to Yocto-4.3.3

- Alassane Yattara
- Alexander Kanavin
- Anuj Mittal
- Baruch Siach
- Bruce Ashfield
- Chen Qi
- Clay Chang
- Enguerrand de Ribaucourt
- Ilya A. Kriveshko
- Jason Andryuk
- Jeremy A. Puhlman
- Joao Marcos Costa

- Jose Quaresma
- Joshua Watt
- Jörg Sommer
- Khem Raj
- Lee Chee Yang
- Markus Volk
- Massimiliano Minella
- Maxin B. John
- Michael Opdenacker
- Ming Liu
- Mingli Yu
- Peter Kjellerstedt
- Peter Marko
- Richard Purdie
- Robert Berger
- Robert Yang
- Rodrigo M. Duarte
- Ross Burton
- Saul Wold
- Simone Weiß
- Soumya Sambu
- Steve Sakoman
- Trevor Gamblin
- Wang Mingyu
- William Lyu
- Xiangyu Chen
- Yang Xu
- Zahir Hussain

### **Repositories / Downloads for Yocto-4.3.3**

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [nanbield](#)



- Tag: `yocto-4.3.3`
- Git Revision: `d3b27346c3a4a7ef7ec517e9d339d22bda74349d`
- Release Artefact: `poky-d3b27346c3a4a7ef7ec517e9d339d22bda74349d`
- sha: `2db39f1bf7bbcee039e9970eed1f6f9233bcc95d675159647c9a2a334fc81eb0`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.3/poky-d3b27346c3a4a7ef7ec517e9d339d22bda74349d.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.3/poky-d3b27346c3a4a7ef7ec517e9d339d22bda74349d.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `nanbield`
- Tag: `yocto-4.3.3`
- Git Revision: `0584d01f623e1f9b0fef4dfa95dd66de6cbfb7b3`
- Release Artefact: `oecore-0584d01f623e1f9b0fef4dfa95dd66de6cbfb7b3`
- sha: `730de0d5744f139322402ff9a6b2483c6ab929f704cec06258ae51de1daebe3d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.3/oecore-0584d01f623e1f9b0fef4dfa95dd66de6cbfb7b3.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.3/oecore-0584d01f623e1f9b0fef4dfa95dd66de6cbfb7b3.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `nanbield`
- Tag: `yocto-4.3.3`
- Git Revision: `49617a253e09baabbf0355bc736122e9549c8ab2`
- Release Artefact: `meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2`
- sha: `2225115b73589cdbf1e491115221035c6a61679a92a93b2a3cf761ff87bf4ecc`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.3/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.3/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.6`
- Tag: `yocto-4.3.3`
- Git Revision: `380a9ac97de5774378ded5e37d40b79b96761a0c`
- Release Artefact: `bitbake-380a9ac97de5774378ded5e37d40b79b96761a0c`
- sha: `78f579b9d29e72d09b6fb10ac62aa925104335e92d2afb3155bc9ab1994e36c1`

- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.3/bitbake-380a9ac97de5774378ded5e37d40b79b96761a0c.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.3/bitbake-380a9ac97de5774378ded5e37d40b79b96761a0c.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: nanbield
- Tag: yocto-4.3.3
- Git Revision: dde4b815db82196af086847f68ee27d7902b4ffa

## 17.8.6 Release notes for Yocto-4.3.4 (Nanbield)

### Security Fixes in Yocto-4.3.4

- bind: Fix CVE-2023-4408, CVE-2023-5517, CVE-2023-5679 and CVE-2023-50387
- gcc: Update *CVE\_STATUS* for CVE-2023-4039 as fixed
- glibc: Fix CVE-2023-6246, CVE-2023-6779 and CVE-2023-6780
- gnutls: Fix CVE-2024-0553 and CVE-2024-0567
- gstreamer: Fix CVE-2024-0444
- libssh2: fix CVE-2023-48795
- libxml2: Fix CVE-2024-25062
- linux-yocto/6.1: Fix CVE-2023-6610, CVE-2023-6915, CVE-2023-46838, CVE-2023-50431, CVE-2024-1085, CVE-2024-1086 and CVE-2024-23849
- linux-yocto/6.1: Ignore CVE-2021-33630, CVE-2021-33631, CVE-2022-36402, CVE-2023-5717, CVE-2023-6200, CVE-2023-35827, CVE-2023-40791, CVE-2023-46343, CVE-2023-46813, CVE-2023-46862, CVE-2023-51042, CVE-2023-51043, CVE-2023-52340, CVE-2024-0562, CVE-2024-0565, CVE-2024-0582, CVE-2024-0584, CVE-2024-0607, CVE-2024-0639, CVE-2024-0641, CVE-2024-0646, CVE-2024-0775 and CVE-2024-22705
- openssl: fix CVE-2024-0727
- python3-jinja2: Fix CVE-2024-22195
- tiff: Fix CVE-2023-6228, CVE-2023-52355 and CVE-2023-52356
- vim: Fix CVE-2024-22667
- wpa-supPLICANT: Fix CVE-2023-52160
- xserver-xorg: Fix CVE-2023-6377, CVE-2023-6478, CVE-2023-6816, CVE-2024-0229, CVE-2024-0408, CVE-2024-0409, CVE-2024-21885 and CVE-2024-21886
- xwayland: Fix CVE-2023-6816, CVE-2024-0408 and CVE-2024-0409
- zlib: Ignore CVE-2023-6992

### Fixes in Yocto-4.3.4

- allarch: Fix allarch corner case
- at-spi2-core: Upgrade to 2.50.1
- bind: Upgrade to 9.18.24
- build-appliance-image: Update to nanbield head revision
- contributor-guide: add notes for tests
- contributor-guide: be more specific about meta-\* trees
- core-image-ptest: Increase disk size to 1.5G for strace ptest image
- cpio: Upgrade to 2.15
- curl: improve run-ptest
- curl: increase test timeouts
- cve-check: Log if *CVE\_STATUS* set but not reported for component
- cve-update-nvd2-native: Add an age threshold for incremental update
- cve-update-nvd2-native: Fix CVE configuration update
- cve-update-nvd2-native: Fix typo in comment
- cve-update-nvd2-native: Remove duplicated CVE\_CHECK\_DB\_FILE definition
- cve-update-nvd2-native: Remove rejected CVE from database
- cve-update-nvd2-native: nvd\_request\_next: Improve comment
- cve\_check: cleanup logging
- cve\_check: handle *CVE\_STATUS* being set to the empty string
- dev-manual: Rephrase spdx creation
- dev-manual: improve descriptions of 'bitbake -S printdiff'
- dev-manual: packages: clarify shared *PR* service constraint
- dev-manual: packages: fix capitalization
- dev-manual: packages: need enough free space
- docs: add initial stylechecks with Vale
- docs: correct sdk installation default path
- docs: document VIRTUAL-RUNTIME variables
- docs: suppress excess use of "following" word
- docs: use "manual page(s)"
- docs: Makefile: remove releases.rst in "make clean"
- externalsrc: fix task dependency for do\_populate\_lic

- glibc: Remove duplicate *CVE\_STATUS* for *CVE-2023-4527*
- glibc: stable 2.38 branch updates (2.38+gtd37c2b20a4)
- gnutls: Upgrade to 3.8.3
- gstreamer1.0: skip a test that is known to be flaky
- gstreamer: Upgrade to 1.22.9
- gtk: Set *CVE\_PRODUCT*
- kernel.bbclass: Set pkg-config variables for building modules
- libxml2: Upgrade to 2.11.7
- linux-firmware: Upgrade to 20240220
- linux-yocto/6.1: update to v6.1.78
- mdadm: Disable ptests
- migration-guides: add release notes for 4.3.3
- migration-guides: add release notes for 4.0.17
- migration-guides: fix release notes for 4.3.3 linux-yocto/6.1 CVE entries
- multilib\_global.bbclass: fix parsing error with no kernel module split
- openssl: fix crash on aarch64 if BTI is enabled but no Crypto instructions
- openssl: Upgrade to 3.1.5
- overlaysfs: add missing closing parenthesis in selftest
- poky.conf: bump version for 4.3.4 release
- profile-manual: usage.rst: fix reference to bug report
- profile-manual: usage.rst: formatting fixes
- profile-manual: usage.rst: further style improvements
- pseudo: Update to pull in gcc14 fix and missing statvfs64 intercept
- python3-jinja2: Upgrade to 3.1.3
- ref-manual: release-process: grammar fix
- ref-manual: system-requirements: update packages to build docs
- ref-manual: tasks: do\_cleanall: recommend using '-f' instead
- ref-manual: tasks: do\_cleansstate: recommend using '-f' instead for a shared sstate
- ref-manual: variables: adding multiple groups in *GROUPADD\_PARAM*
- ref-manual: variables: add documentation of the variable *SPDX\_NAMESPACE\_PREFIX*
- reproducible: Fix race with externalsrc/devtool over lockfile
- sdk-manual: extensible: correctly describe separate build-sysroots tasks in direct sdk workflows

- tzdata : Upgrade to 2024a
- udev-extraconf: fix unmount directories containing octal-escaped chars
- vim: Upgrade to v9.0.2190
- wireless-regdb: Upgrade to 2024.01.23
- xserver-xorg: Upgrade to 21.1.11
- xwayland: Upgrade to 23.2.4
- yocto-uninative: Update to 4.4 for glibc 2.39

#### Known Issues in Yocto-4.3.4

- N/A

#### Contributors to Yocto-4.3.4

- Alex Kiernan
- Alexander Kanavin
- Alexander Sverdlin
- Baruch Siach
- BELOUARGA Mohamed
- Benjamin Bara
- Bruce Ashfield
- Chen Qi
- Claus Stovgaard
- Dhairya Nagodra
- Geoff Parker
- Johan Bezem
- Jonathan GUILLOT
- Julien Stephan
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Luca Ceresoli
- Martin Jansa
- Michael Halstead
- Michael Opdenacker
- Munehisa Kamata

- Pavel Zhukov
- Peter Marko
- Priyal Doshi
- Richard Purdie
- Robert Joslyn
- Ross Burton
- Simone Weiß
- Soumya Sambu
- Steve Sakoman
- Tim Orling
- Wang Mingyu
- Yoann Congal
- Yogita Urade

## Repositories / Downloads for Yocto-4.3.4

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `nanbield`
- Tag: `yocto-4.3.4`
- Git Revision: `7b8aa378d069ee31373f22caba3bd7fc7863f447`
- Release Artefact: `poky-7b8aa378d069ee31373f22caba3bd7fc7863f447`
- sha: `0cb14125f215cc9691cff43982e2c540a5b6018df4ed25c10933135b5bf21d0f`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.4/poky-7b8aa378d069ee31373f22caba3bd7fc7863f447.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.4/poky-7b8aa378d069ee31373f22caba3bd7fc7863f447.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `nanbield`
- Tag: `yocto-4.3.4`
- Git Revision: `d0e68072d138ccc1fb5957fdc46a91871eb6a3e1`
- Release Artefact: `oecore-d0e68072d138ccc1fb5957fdc46a91871eb6a3e1`
- sha: `d311fe22ff296c466f9bea1cd26343baee5630bc37f3dda42f2d9d8cc99e3add`

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.4/oecore-d0e68072d138ccc1fb5957fdc46a91871eb6a3e1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.4/oecore-d0e68072d138ccc1fb5957fdc46a91871eb6a3e1.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: nanbield
- Tag: yocto-4.3.4
- Git Revision: 49617a253e09baabbf0355bc736122e9549c8ab2
- Release Artefact: meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2
- sha: 2225115b73589cdf1e491115221035c6a61679a92a93b2a3cf761ff87bf4ecc
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.4/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.4/meta-mingw-49617a253e09baabbf0355bc736122e9549c8ab2.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.6
- Tag: yocto-4.3.4
- Git Revision: 380a9ac97de5774378ded5e37d40b79b96761a0c
- Release Artefact: bitbake-380a9ac97de5774378ded5e37d40b79b96761a0c
- sha: 78f579b9d29e72d09b6fb10ac62aa925104335e92d2afb3155bc9ab1994e36c1
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.3.4/bitbake-380a9ac97de5774378ded5e37d40b79b96761a0c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.3.4/bitbake-380a9ac97de5774378ded5e37d40b79b96761a0c.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: nanbield
- Tag: yocto-4.3.4
- Git Revision: 05d08b0bbaef760157c8d35a78d7405bc5ffce55

## 17.9 Release 4.2 (mickledore)

### 17.9.1 Release 4.2 (mickledore)

#### Migration notes for 4.2 (mickledore)

This section provides migration information for moving to the Yocto Project 4.2 Release (codename "mickledore") from the prior release.

## Supported distributions

This release supports running BitBake on new GNU/Linux distributions:

- Fedora 36 and 37
- AlmaLinux 8.7 and 9.1
- OpenSuse 15.4

On the other hand, some earlier distributions are no longer supported:

- Debian 10.x
- Fedora 34 and 35
- AlmaLinux 8.5

See *all supported distributions*.

## Python 3.8 is now the minimum required Python version

BitBake and OpenEmbedded-Core now require Python 3.8 or newer, making it a requirement to use a distribution providing at least this version, or to install a *buildtools* tarball.

## gcc 8.0 is now the minimum required GNU C compiler version

This version, released in 2018, is a minimum requirement to build the `mesa-native` recipe and as the latter is in the default dependency chain when building QEMU this has now been made a requirement for all builds.

In the event that your host distribution does not provide this or a newer version of gcc, you can install a *buildtools-extended* tarball.

## Fetching the NVD vulnerability database through the 2.0 API

This new version adds a new fetcher for the NVD database using the 2.0 API, as the 1.0 API will be retired in 2023.

The implementation changes as little as possible, keeping the current database format (but using a different database file for the transition period), with a notable exception of not using the META table.

Here are minor changes that you may notice:

- The database starts in 1999 instead of 2002
- The complete fetch is longer (30 minutes typically)

## Rust: mandatory checksums for crates

This release now supports checksums for Rust crates and makes them mandatory for each crate in a recipe. See *python3\_bcrypt recipe changes* for example.

The `cargo-update-recipe-crates` utility *has been extended* to include such checksums. So, in case you need to add the list of checksums to a recipe just inheriting the *cargo* class so far, you can follow these steps:

1. Make the recipe inherit *cargo-update-recipe-crates*
2. Remove all `crate://` lines from the recipe



3. Create an empty `${BPN}-crates.inc` file and make your recipe require it
4. Execute `bitbake -c update_crates your_recipe`
5. Copy and paste the output of BitBake about the missing checksums into the `${BPN}-crates.inc` file.

## Python library code extensions

BitBake in this release now supports a new `addpylib` directive to enable Python libraries within layers.

This directive should be added to your layer configuration as in the below example from `meta/conf/layer.conf`:

```
addpylib ${LAYERDIR}/lib oe
```

Layers currently adding a `lib` directory to extend Python library code should now use this directive as `BBPATH` is not going to be added automatically by OE-Core in future. Note that the directives are immediate operations, so it does make modules available for use sooner than the current `BBPATH`-based approach.

For more information, see [Extending Python Library Code](#).

## Removed variables

The following variables have been removed:

- `SERIAL_CONSOLE`, deprecated since version 2.6, replaced by `SERIAL_CONSOLES`.
- `PACKAGEBUILDPKGD`, a mostly internal variable in the `package` class was rarely used to customise packaging. If you were using this in your custom recipes or `bbappends`, you will need to switch to using `PACKAGE_PREPROCESS_FUNCS` or `PACKAGESPLITFUNCS` instead.

## Removed recipes

The following recipes have been removed in this release:

- `python3-picobuild`: after switching to `python3-build`
- `python3-strict-rfc3339`: unmaintained and not needed by anything in `openembedded-core` or `meta-openembedded`.
- `linux-yocto`: removed version 5.19 recipes (6.1 and 5.15 still provided)

## Removed classes

The following classes have been removed in this release:

- `rust-bin`: no longer used
- `package_tar`: could not be used for actual packaging, and thus not particularly useful.

## LAYERSERIES\_COMPAT for custom layers and devtool workspace

Some layer maintainers have been setting `LAYERSERIES_COMPAT` in their layer's `conf/layer.conf` to the value of `LAYERSERIES_CORENAMES` to effectively bypass the compatibility check - this is no longer permitted. Layer maintainers should set `LAYERSERIES_COMPAT` appropriately to help users understand the compatibility status of the layer.

Additionally, the `LAYERSERIES_COMPAT` value for the devtool workspace layer is now set at the time of creation, thus if you upgrade with the workspace layer enabled and you wish to retain it, you will need to manually update the `LAYERSERIES_COMPAT` value in `workspace/conf/layer.conf` (or remove the path from `BBLAYERS` in `build/conf/bblayers.conf` and delete/move the `workspace` directory out of the way if you no longer need it).

## runqemu now limits slirp host port forwarding to localhost

With default slirp port forwarding configuration in runqemu, qemu previously listened on TCP ports 2222 and 2323 on all IP addresses available on the build host. Most use cases with runqemu only need it for localhost and it is not safe to run qemu images with root login without password enabled and listening on all available, possibly Internet reachable network interfaces. Thus, in this release we limit qemu port forwarding to localhost (127.0.0.1).

However, if you need the qemu machine to be reachable from the network, then it can be enabled via `build/conf/local.conf` or machine config variable `QB_SLIRP_OPT`:

```
QB_SLIRP_OPT = "-netdev user,id=net0,hostfwd=tcp::2222-:22"
```

## Patch QA checks

The QA checks for patch fuzz and Upstream-Status have been reworked slightly in this release. The Upstream-Status checking is now configurable from `WARN_QA` / `ERROR_QA` (`patch-status-core` for the core layer, and `patch-status-noncore` for other layers).

The `patch-fuzz` and `patch-status-core` checks are now in the default value of `ERROR_QA` so that they will cause the build to fail if triggered. If you prefer to avoid this you will need to adjust the value of `ERROR_QA` in your configuration as desired.

## Native/nativesdk mesa usage and graphics drivers

This release includes mesa 23.0, and with that mesa release it is not longer possible to use drivers from the host system, as mesa upstream has added strict checks for matching builds between drivers and libraries that load them.

This is particularly relevant when running QEMU built within the build system. A check has been added to runqemu so that there is a helpful error when there is no native/nativesdk opengl/virgl support available.

To support this, a number of drivers have been enabled when building `mesa-native`. The one major dependency pulled in by this change is `llvm-native` which will add a few minutes to the build on a modern machine. If this is undesirable, you can set the value of `DISTRO_FEATURES_NATIVE` in your configuration such that `opengl` is excluded.

## Miscellaneous changes

- The `IMAGE_NAME` variable is now set based on `IMAGE_LINK_NAME`. This means that if you are setting `IMAGE_LINK_NAME` to "" to disable unversioned image symlink creation, you also now need to set `IMAGE_NAME` to still have a reasonable value e.g.:

```
IMAGE_LINK_NAME = ""
IMAGE_NAME = "${IMAGE_BASENAME}${IMAGE_MACHINE_SUFFIX}${IMAGE_VERSION_SUFFIX}"
```

- In `/etc/os-release`, the `VERSION_CODENAME` field is now used instead of `DISTRO_CODENAME` (though its value is still set from the `DISTRO_CODENAME` variable) for better conformance to standard `os-release` usage. If you have runtime code reading this from `/etc/os-release` it may need to be updated.
- The `kmod` recipe now enables OpenSSL support by default in order to support module signing. If you do not need this and wish to reclaim some space/avoid the dependency you should set `PACKAGECONFIG` in a `kmod` `bbappend` (or `PACKAGECONFIG:pn-kmod` at the configuration level) to exclude `openssl`.
- The `OEBasic` signature handler (see `BB_SIGNATURE_HANDLER`) has been removed. It is unlikely that you would have selected to use this, but if you have you will need to remove this setting.
- The `package` class now checks if package names conflict via `PKG:${PN}` override during `do_package`. If you receive the associated error you will need to address the `PKG` usage so that the conflict is resolved.
- `openssh` no longer uses `RRECOMMENDS` to pull in `rng-tools`, since `rngd` is no longer needed as of Linux kernel 5.6. If you still need `rng-tools` installed for other reasons, you should add `rng-tools` explicitly to your image. If you additionally need `rngd` to be started as a service you will also need to add the `rng-tools-service` package as that has been split out.
- The `cups` recipe no longer builds with the web interface enabled, saving ~1.8M of space in the final image. If you wish to enable it, you should set `PACKAGECONFIG` in a `cups` `bbappend` (or `PACKAGECONFIG:pn-cups` at the configuration level) to include `webif`.
- The `scons` class now passes a `MAXLINELENGTH` argument to `scons` in order to fix an issue with `scons` and command line lengths when `ccache` is enabled. However, some recipes may be using older `scons` versions which don't support this argument. If that is the case you can set the following in the recipe in order to disable this:

```
SCONS_MAXLINELENGTH = ""
```

## 17.9.2 Release notes for 4.2 (mickledore)

### New Features / Enhancements in 4.2

- Linux kernel 6.1, glibc 2.37 and ~350 other recipe upgrades
- Python 3.8+ and GCC 8.0+ are now the minimum required versions on the build host. For host distributions that do not provide it, this is included as part of the `buildtools` tarball.
- BitBake in this release now supports a new `addpylib` directive to enable Python libraries within layers. For more information, see [Extending Python Library Code](#).

This directive should be added to your layer configuration as in the below example from `meta/conf/layer.conf`:

```
addpylib ${LAYERDIR}/lib oe
```

- BitBake has seen multiple internal changes that may improve memory and disk usage as well as parsing time, in particular:
  - BitBake's Cooker server is now multithreaded.
  - Ctrl+C can now be used to interrupt some long-running operations that previously ignored it.
  - BitBake's cache has been extended to include more hash debugging data, but has also been optimized to [compress cache data](#).
  - BitBake's UI will now ping the server regularly to ensure it is still alive.
- New variables:
  - `VOLATILE_TMP_DIR` allows to specify whether `/tmp` should be on persistent storage or in RAM.
  - `SPDX_CUSTOM_ANNOTATION_VARS` allows to add specific comments to the `SPDX` description of a recipe.
- Rust improvements:
  - This release adds Cargo support on the target, and includes automated QA tests for this functionality.
  - It also supports checksums for Rust crates and makes them mandatory for each crate in a recipe.
  - New [cargo-update-recipe-crates](#) class to enable updating `SRC_URI` crate lists from `Cargo.lock`
  - Enabled building Rust for baremetal targets
  - You can now also easily select to build beta or nightly versions of Rust with a new `RUST_CHANNEL` variable (use at own risk)
  - Support for local GitHub repos in `SRC_URI` as replacements for Cargo dependencies
  - Use built-in Rust targets for `-native` builds to save several minutes building the Rust toolchain
- Architecture-specific enhancements:
  - This release adds initial support for the [LoongArch](#) (`loongarch64`) architecture, though there is no testing for it yet.
  - New `x86-64-v3` tunes (AVX, AVX2, BMI1, BMI2, F16C, FMA, LZCNT, MOVBE, XSAVE)
  - go: add support to build on `ppc64le`
  - rust: `rustfmt` now working and installed for `riscv32`
  - `libpng`: enable NEON for `aarch64` to ensure consistency with `arm32`.
  - `baremetal-helloworld`: Enable `x86` and `x86-64` ports
- Kernel-related enhancements:
  - Added some support for building 6.2/6.3-rc kernels
  - `linux-yocto-dev`: mark as compatible with `qemuarm64` and `qemuarmv5`

- Add kernel specific OBJCOPY to help switching toolchains cleanly for kernel build between gcc and clang
- New core recipes:
  - debugedit
  - gtk4 (import from meta-gnome)
  - gcr: add recipe for gcr-4
  - graphene (import from meta-oe)
  - libc-test
  - libportal (import from meta-gnome)
  - libslirp
  - libtest-fatal-perl
  - libtest-warnings-perl (import from meta-perl)
  - libtry-tiny-perl
  - python3-build
  - python3-pyproject-hooks
  - python3-hatch-fancy-pypi-readme
  - python3-unittest-automake
- QEMU/runqemu enhancements:
  - Set QB\_SMP with ?= to make it easier to modify
  - Set QB\_CPU with ?= to make it easier to modify (x86 configuration only)
  - New QB\_NFSROOTFS\_EXTRA\_OPT to allow extra options to be appended to the NFS rootfs options in kernel boot args, e.g. "wsize=4096,rsize=4096"
  - New QB\_SETUP\_CMD and QB\_CLEANUP\_CMD to enable running custom shell setup and cleanup commands before and after QEMU.
  - QB\_DEFAULT\_KERNEL now defaults to pick the bundled initramfs kernel image if the Linux kernel image is generated with *INITRAMFS\_IMAGE\_BUNDLE* set to "1"
  - Split out the QEMU guest agent to its own qemu-guest-agent package
  - runqemu: new guestagent option to enable communication with the guest agent
  - runqemu: respect *IMAGE\_LINK\_NAME* when searching for image
- Image-related enhancements:
  - Add 7-Zip support in image conversion types (7zip)
  - New *IMAGE\_MACHINE\_SUFFIX* variable to allow easily removing machine name suffix from image file names
- wic Image Creator enhancements:

- `bootimg-efi.py`: add support for directly loading Linux kernel UEFI stub
- `bootimg-efi.py`: implement `--include-path`
- Allow usage of `fstype=none` to specify an unformatted partition
- Implement repeatable disk identifiers based on *SOURCE\_DATE\_EPOCH*
- FIT image related improvements:
  - FIT image signing support has been reworked to remove interdependencies and make it more easily extensible
  - Skip FDT section creation for applicable symlinks to avoid the same dtb being duplicated
  - New *FIT\_CONF\_DEFAULT\_DTB* variable to enable selecting default dtb when multiple dtbs exist
- SDK-related improvements:
  - Extended the following recipes to nativesdk:
    - \* `bc`
    - \* `gi-docgen`
    - \* `gperf`
    - \* `python3-iniconfig`
    - \* `python3-atomicwrites`
    - \* `python3-markdown`
    - \* `python3-smartypants`
    - \* `python3-typogrify`
    - \* `ruby`
    - \* `unifdef`
  - New *SDK\_ZIP\_OPTIONS* variable to enable passing additional options to the zip command when preparing the SDK zip archive
  - New Rust SDK target packagegroup (`packagegroup-rust-sdk-target`)
- Testing:
  - The ptest images have changed structure in this release. The underlying `core-image-ptest` recipe now uses *BBCLASSEXTEND* to create a variant for each ptest enabled recipe in OE-Core.

For example, this means that `core-image-ptest-bzip2`, `core-image-ptest-lttng-tools` and many more image targets now exist and can be built/tested individually.

The `core-image-ptest-all` and `core-image-ptest-fast` targets are now wrappers that target groups of individual images and means that the tests can be executed in parallel during our automated testing. This also means the dependencies are more accurately tested.
  - It is now possible to track regression changes between releases using `yocto_testresults_query.py`, which is a thin wrapper over `resulttool`. Here is an example command, which allowed to spot and fix a regression in the quilt ptest:

```
yocto_testresults_query.py regression-report 4.2_M1 4.2_M2
```

See this [blog post](#) about regression detection.

- This release adds support for parallel ptest execution with a ptest per image. This takes ptest execution time from 3.5 hours to around 45 minutes on the autobuilder.
- Basic Rust compile/run and cargo tests
- New `python3-unittest-automake` recipe which provides modules for pytest and unittest to adjust their output to automake-style for easier integration with the ptest system.
- ptest support added to `bc`, `cpio` and `gnutls`, and fixes made to ptests in numerous other recipes.
- `ptest-runner` now adds a non-root "ptest" user to run tests.
- `resulttool`: add a `--list-ptest` option to the `log` subcommand to list ptest names in a results file
- `resulttool`: `regression`: add metadata filtering for `oeselftest`
- New *PACKAGECONFIG* options in the following recipes:
  - `at-spi2-core`
  - `base-passwd`
  - `cronie`
  - `cups`
  - `curl`
  - `file`
  - `gststreamer1.0-plugins-good`
  - `gtk+3`
  - `iproute2`
  - `libsdl2`
  - `libtiff`
  - `llvm`
  - `mesa`
  - `psmisc`
  - `qemu`
  - `sudo`
  - `systemd`
  - `tiff`
  - `util-linux`
- Extended the following recipes to native:

- iso-codes
  - libxkbcommon
  - p11-kit
  - python3-atomicwrites
  - python3-dbusmock
  - python3-iniconfig
  - xkeyboard-config
- Utility script changes:
    - devtool: ignore patch-fuzz errors when extracting source in order to enable fixing fuzz issues
    - oe-setup-layers: make efficiently idempotent
    - oe-setup-layers: print a note about submodules if present
    - New buildstats-summary script to show a summary of the buildstats data
    - *report-error* class: catch `Nothing PROVIDES error`
    - combo-layer: add `sync-revs` command
    - convert-overrides: allow command-line customizations
  - bitbake-layers improvements:
    - layerindex-fetch: checkout layer(s) branch when clone exists
    - create: add `-a/--add-layer` option to add layer to *build/conf/bblayers.conf* after creating layer
    - show-layers: improve output layout
  - Other BitBake improvements:
    - Inline Python snippets can now include dictionary expressions
    - Evaluate the value of export/unexport/network flags so that they can be reset to "0"
    - Make *EXCLUDE\_FROM\_WORLD* boolean so that it can be reset to "0"
    - Support int values in `bb.utils.to_boolean()` in addition to strings
    - bitbake-getvar: Add a quiet command line argument
    - Allow the @ character in variable flag names
    - Python library code will now be included when calculating task hashes
    - fetch2/npmsh: add more short forms for git operations
    - Display a warning when `SRCREV = "${AUTOREV}"` is set too late to be effective
    - Display all missing *SRC\_URI* checksums at once
    - Improve error message for a missing multiconfig
    - Switch to a new *BB\_CACHEDIR* variable for codeparser cache location



- Mechanism introduced to reduce the codeparser cache unnecessarily growing in size
- Packaging changes:
  - `rng-tools` is no longer recommended by `openssh`, and the `rng-tools` service files have been split out to their own package
  - `linux-firmware`: split `rtl8761` and `amdgpu` firmware
  - `linux-firmware`: add new firmware file to `${PN}-qcom-adreno-a530`
  - `iproute2`: separate `routel` and add Python dependency
  - `xinetd`: move `xconv.pl` script to separate package
  - `perf`: enable debug/source packaging
- Prominent documentation updates:
  - Substantially expanded the "*Verifica delle Vulnerabilità*" section.
  - Added a new "*Creating a Software Bill of Materials*" section about SPDX SBoM generation.
  - Expanded "*Selecting an Initialization Manager*" documentation.
  - New section about *Versioni con Supporto a Lungo Termine*.
  - System Requirements: details about *RAM Minima di Sistema*.
  - Details about *Building a Meson Package* and the *meson* class.
  - Documentation about how to write recipes for Rust programs. See the *cargo* class.
  - Documentation about how to write recipes for Go programs. See the *go* class.
  - Variable index: added references to variables only documented in the BitBake manual. All variables should be easy to access through the Yocto Manual variable index.
  - Expanded the description of the *BB\_NUMBER\_THREADS* variable.
- Miscellaneous changes:
  - Supporting 64 bit dates on 32 bit platforms: several packages have been updated to pass year 2038 tests, and a QA check for 32 bit time and file offset functions has been added (default off)
  - Patch fuzz/Upstream-Status checking has been reworked:
    - \* Upstream-Status checking is now configurable from *WARN\_QA/ERROR\_QA* (*patch-status-core*)
    - \* Can now be enabled for non-core layers (*patch-status-noncore*)
    - \* *patch-fuzz* is now in *ERROR\_QA* by default, and actually stops the build
  - Many packages were updated to add large file support.
  - `vulkan-loader`: allow headless targets to build the loader
  - `dhcpd`: fix to work with `systemd`
  - `u-boot`: add `/boot` to *SYSROOT\_DIRS* to allow boot files to be used by other recipes
  - `linux-firmware`: don't put the firmware into the sysroot

- cups: add *PACKAGECONFIG* to control web interface and default to off
- buildtools-tarball: export certificates to python and curl
- yocto-check-layer: allow OE-Core to be tested
- yocto-check-layer: check for patch file upstream status
- boost: enable building Boost .URL library
- native: drop special variable handling
- Poky: make it easier to set *INIT\_MANAGER* from local.conf
- *create-spdx*: add support for custom annotations (*SPDX\_CUSTOM\_ANNOTATION\_VARS*)
- *create-spdx*: report downloads as separate packages
- *create-spdx*: remove the top-level image SPDX file and the JSON index file from *DEPLOYDIR* to avoid confusion
- os-release: replace `DISTRO_CODENAME` with `VERSION_CODENAME` (still set from *DISTRO\_CODENAME*)
- weston: add kiosk shell
- *overlaysfs*: Allow unused mount points
- sstatesig: emit more helpful error message when not finding sstate manifest
- *pypi.bbclass*: Set *SRC\_URI* downloadfilename with an optional prefix
- poky-bleeding distro: update and rework
- *package.bbclass*: check if package names conflict via `PKG:${PN}` override in *do\_package*
- cve-update-nvd2-native: new NVD CVE database fetcher using the 2.0 API
- *mirrors* class: use shallow tarball for binutils-native/nativesdk-binutils
- meta/conf: move default configuration templates into meta/conf/templates/default
- binutils: enable `--enable-new-dtags` as per many Linux distributions
- base-files: drop localhost.localdomain from hosts file as per many Linux distributions
- packagegroup-core-boot: make `init-ifupdown` package a recommendation

## Known Issues in 4.2

- N/A

## Recipe License changes in 4.2

The following corrections have been made to the *LICENSE* values set by recipes:

- curl: set *LICENSE* appropriately to curl as it is a special derivative of the MIT/X license, not exactly that license.
- libgit2: added Zlib, ISC, LGPL-2.1-or-later and CC0-1.0 to *LICENSE* covering portions of the included code.

- `linux-firmware`: set package *LICENSE* appropriately for all qcom packages

## Security Fixes in 4.2

- `binutils`: CVE-2022-4285, CVE-2023-25586
- `curl`: CVE-2022-32221, CVE-2022-35260, CVE-2022-42915, CVE-2022-42916
- `epiphany`: CVE-2023-26081
- `expat`: CVE-2022-43680
- `ffmpeg`: CVE-2022-3964, CVE-2022-3965
- `git`: CVE-2022-39260, CVE-2022-41903, CVE-2022-23521, CVE-2022-41953 (ignored)
- `glibc`: CVE-2023-25139 (ignored)
- `go`: CVE-2023-24532, CVE-2023-24537
- `grub2`: CVE-2022-2601, CVE-2022-3775, CVE-2022-28736
- `inetutils`: CVE-2019-0053
- `less`: CVE-2022-46663
- `libarchive`: CVE-2022-36227
- `libinput`: CVE-2022-1215
- `libpam`: CVE-2022-28321
- `libpng`: CVE-2019-6129
- `libx11`: CVE-2022-3554
- `openssh`: CVE-2023-28531
- `openssl`: CVE-2022-3358, CVE-2022-3786, CVE-2022-3602, CVE-2022-3996, CVE-2023-0286, CVE-2022-4304, CVE-2022-4203, CVE-2023-0215, CVE-2022-4450, CVE-2023-0216, CVE-2023-0217, CVE-2023-0401, CVE-2023-0464
- `ppp`: CVE-2022-4603
- `python3-cryptography{-vectors}`: CVE-2022-3602, CVE-2022-3786, CVE-2023-23931
- `python3`: CVE-2022-37460
- `qemu`: CVE-2022-3165
- `rust`: CVE-2022-46176
- `rxvt-unicode`: CVE-2022-4170
- `screen`: CVE-2023-24626
- `shadow`: CVE-2023-29383, CVE-2016-15024 (ignored)
- `sudo`: CVE-2022-43995
- `systemd`: CVE-2022-4415 (ignored)
- `tar`: CVE-2022-48303

- tiff: CVE-2022-3599, CVE-2022-3597, CVE-2022-3626, CVE-2022-3627, CVE-2022-3570, CVE-2022-3598, CVE-2022-3970, CVE-2022-48281
- vim: CVE-2022-3352, CVE-2022-4141, CVE-2023-0049, CVE-2023-0051, CVE-2023-0054, CVE-2023-0288, CVE-2023-1127, CVE-2023-1170, CVE-2023-1175, CVE-2023-1127, CVE-2023-1170, CVE-2023-1175, CVE-2023-1264, CVE-2023-1355, CVE-2023-0433, CVE-2022-47024, CVE-2022-3705
- xdg-utils: CVE-2022-4055
- xserver-xorg: CVE-2022-3550, CVE-2022-3551, CVE-2023-1393, CVE-2023-0494, CVE-2022-3553 (ignored)

## **Recipe Upgrades in 4.2**

- acpid: upgrade 2.0.33 -> 2.0.34
- adwaita-icon-theme: update 42.0 -> 43
- alsa-lib: upgrade 1.2.7.2 -> 1.2.8
- alsa-ucm-conf: upgrade 1.2.7.2 -> 1.2.8
- alsa-utils: upgrade 1.2.7 -> 1.2.8
- apr: update 1.7.0 -> 1.7.2
- apr-util: update 1.6.1 -> 1.6.3
- argp-standalone: replace with a maintained fork
- at-spi2-core: upgrade 2.44.1 -> 2.46.0
- autoconf-archive: upgrade 2022.09.03 -> 2023.02.20
- babeltrace: upgrade 1.5.8 -> 1.5.11
- base-passwd: Update to 3.6.1
- bash: update 5.1.16 -> 5.2.15
- bind: upgrade 9.18.7 -> 9.18.12
- binutils: Upgrade to 2.40 release
- bluez: update 5.65 -> 5.66
- boost-build-native: update 1.80.0 -> 1.81.0
- boost: upgrade 1.80.0 -> 1.81.0
- btrfs-tools: upgrade 5.19.1 -> 6.1.3
- busybox: 1.35.0 -> 1.36.0
- ccache: upgrade 4.6.3 -> 4.7.4
- cmake: update 3.24.0 -> 3.25.2
- cracklib: upgrade to v2.9.10
- curl: upgrade 7.86.0 -> 8.0.1

- dbus: upgrade 1.14.0 -> 1.14.6
- diffoscope: upgrade 221 -> 236
- diffstat: upgrade 1.64 -> 1.65
- diffutils: update 3.8 -> 3.9
- dos2unix: upgrade 7.4.3 -> 7.4.4
- dpkg: update 1.21.9 -> 1.21.21
- dropbear: upgrade 2022.82 -> 2022.83
- dtc: upgrade 1.6.1 -> 1.7.0
- e2fsprogs: upgrade 1.46.5 -> 1.47.0
- ed: upgrade 1.18 -> 1.19
- elfutils: update 0.187 -> 0.188
- ell: upgrade 0.53 -> 0.56
- enchant2: upgrade 2.3.3 -> 2.3.4
- encodings: update 1.0.6 -> 1.0.7
- epiphany: update 42.4 -> 43.1
- ethtool: upgrade 5.19 -> 6.2
- expat: upgrade to 2.5.0
- ffmpeg: upgrade 5.1.1 -> 5.1.2
- file: upgrade 5.43 -> 5.44
- flac: update 1.4.0 -> 1.4.2
- font-alias: update 1.0.4 -> 1.0.5
- fontconfig: upgrade 2.14.0 -> 2.14.2
- font-util: upgrade 1.3.3 -> 1.4.0
- freetype: update 2.12.1 -> 2.13.0
- gawk: update 5.1.1 -> 5.2.1
- gcr3: update 3.40.0 -> 3.41.1
- gcr: rename gcr -> gcr3
- gdb: Upgrade to 13.1
- gdk-pixbuf: upgrade 2.42.9 -> 2.42.10
- gettext: update 0.21 -> 0.21.1
- ghostscript: update 9.56.1 -> 10.0.0
- gi-docgen: upgrade 2022.1 -> 2023.1

- git: upgrade 2.37.3 -> 2.39.2
- glib-2.0: update 2.72.3 -> 2.74.6
- glibc: upgrade to 2.37 release + stable updates
- glib-networking: update 2.72.2 -> 2.74.0
- glslang: upgrade 1.3.236.0 -> 1.3.239.0
- gnu-config: upgrade to latest revision
- gnupg: upgrade 2.3.7 -> 2.4.0
- gnutls: upgrade 3.7.7 -> 3.8.0
- gobject-introspection: upgrade 1.72.0 -> 1.74.0
- go: update 1.19 -> 1.20.1
- grep: update 3.7 -> 3.10
- gsettings-desktop-schemas: upgrade 42.0 -> 43.0
- gstreamer1.0: upgrade 1.20.3 -> 1.22.0
- gtk+3: upgrade 3.24.34 -> 3.24.36
- gtk4: update 4.8.2 -> 4.10.0
- harfbuzz: upgrade 5.1.0 -> 7.1.0
- hdparm: update 9.64 -> 9.65
- help2man: upgrade 1.49.2 -> 1.49.3
- icu: update 71.1 -> 72-1
- ifupdown: upgrade 0.8.37 -> 0.8.41
- igt-gpu-tools: upgrade 1.26 -> 1.27.1
- inetutils: upgrade 2.3 -> 2.4
- init-system-helpers: upgrade 1.64 -> 1.65.2
- iproute2: upgrade 5.19.0 -> 6.2.0
- iptables: update 1.8.8 -> 1.8.9
- iputils: update to 20221126
- iso-codes: upgrade 4.11.0 -> 4.13.0
- jquery: upgrade 3.6.0 -> 3.6.3
- kexec-tools: upgrade 2.0.25 -> 2.0.26
- kmscube: upgrade to latest revision
- libarchive: upgrade 3.6.1 -> 3.6.2
- libbsd: upgrade 0.11.6 -> 0.11.7

- libcap: upgrade 2.65 -> 2.67
- libdnf: update 0.69.0 -> 0.70.0
- libdrm: upgrade 2.4.113 -> 2.4.115
- libedit: upgrade 20210910-3.1 -> 20221030-3.1
- libepoxy: update 1.5.9 -> 1.5.10
- libffi: upgrade 3.4.2 -> 3.4.4
- libfontenc: upgrade 1.1.6 -> 1.1.7
- libgit2: upgrade 1.5.0 -> 1.6.3
- libgpg-error: update 1.45 -> 1.46
- libhandy: update 1.6.3 -> 1.8.1
- libical: upgrade 3.0.14 -> 3.0.16
- libice: update 1.0.10 -> 1.1.1
- libidn2: upgrade 2.3.3 -> 2.3.4
- libinput: upgrade 1.19.4 -> 1.22.1
- libjpeg-turbo: upgrade 2.1.4 -> 2.1.5.1
- libksba: upgrade 1.6.0 -> 1.6.3
- libmicrohttpd: upgrade 0.9.75 -> 0.9.76
- libmodule-build-perl: update 0.4231 -> 0.4232
- libmpc: upgrade 1.2.1 -> 1.3.1
- libnewt: update 0.52.21 -> 0.52.23
- libnotify: upgrade 0.8.1 -> 0.8.2
- libpcap: upgrade 1.10.1 -> 1.10.3
- libpciaccess: update 0.16 -> 0.17
- libpcre2: upgrade 10.40 -> 10.42
- libpipeline: upgrade 1.5.6 -> 1.5.7
- libpng: upgrade 1.6.38 -> 1.6.39
- libpsl: upgrade 0.21.1 -> 0.21.2
- librepo: upgrade 1.14.5 -> 1.15.1
- libsdl2: upgrade 2.24.1 -> 2.26.3
- libsm: 1.2.3 > 1.2.4
- libsndfile1: upgrade 1.1.0 -> 1.2.0
- libsolve: upgrade 0.7.22 -> 0.7.23

- libsoup-2.4: upgrade 2.74.2 -> 2.74.3
- libsoup: upgrade 3.0.7 -> 3.2.2
- libtest-fatal-perl: upgrade 0.016 -> 0.017
- libtest-needs-perl: upgrade 0.002009 -> 0.002010
- libunistring: upgrade 1.0 -> 1.1
- liburcu: upgrade 0.13.2 -> 0.14.0
- liburi-perl: upgrade 5.08 -> 5.17
- libva: upgrade 2.15.0 -> 2.16.0
- libva-utils: upgrade 2.15.0 -> 2.17.1
- libwebp: upgrade 1.2.4 -> 1.3.0
- libwpe: upgrade 1.12.3 -> 1.14.1
- libx11: 1.8.1 -> 1.8.4
- libx11-compose-data: 1.6.8 -> 1.8.4
- libxau: upgrade 1.0.10 -> 1.0.11
- libxcomposite: update 0.4.5 -> 0.4.6
- libxcrypt-compat: upgrade 4.4.30 -> 4.4.33
- libxcrypt: upgrade 4.4.28 -> 4.4.30
- libxdamage: update 1.1.5 -> 1.1.6
- libxdmcp: update 1.1.3 -> 1.1.4
- libxext: update 1.3.4 -> 1.3.5
- libxft: update 2.3.4 -> 2.3.6
- libxft: upgrade 2.3.6 -> 2.3.7
- libxinerama: update 1.1.4 -> 1.1.5
- libxkbcommon: upgrade 1.4.1 -> 1.5.0
- libxkbfile: update 1.1.0 -> 1.1.1
- libxkbfile: upgrade 1.1.1 -> 1.1.2
- libxml2: upgrade 2.9.14 -> 2.10.3
- libxmu: update 1.1.3 -> 1.1.4
- libxpm: update 3.5.13 -> 3.5.15
- libxrandr: update 1.5.2 -> 1.5.3
- libxrender: update 0.9.10 -> 0.9.11
- libxres: update 1.2.1 -> 1.2.2



- libxscrnsaver: update 1.2.3 -> 1.2.4
- libxshmfence: update 1.3 -> 1.3.2
- libxslt: upgrade 1.1.35 -> 1.1.37
- libxtst: update 1.2.3 -> 1.2.4
- libxv: update 1.0.11 -> 1.0.12
- libxxf86vm: update 1.1.4 -> 1.1.5
- lighttpd: upgrade 1.4.66 -> 1.4.69
- linux-firmware: upgrade 20220913 -> 20230210
- linux-libc-headers: bump to 6.1
- linux-yocto/5.15: update genericx86\* machines to v5.15.103
- linux-yocto/5.15: update to v5.15.108
- linux-yocto/6.1: update to v6.1.25
- linux-yocto-dev: bump to v6.3
- linux-yocto-rt/5.15: update to -rt59
- linux-yocto-rt/6.1: update to -rt7
- llvm: update 14.0.6 -> 15.0.7
- log4cplus: upgrade 2.0.8 -> 2.1.0
- logrotate: upgrade 3.20.1 -> 3.21.0
- lsof: upgrade 4.95.0 -> 4.98.0
- ltp: upgrade 20220527 -> 20230127
- lttnng-modules: upgrade 2.13.4 -> 2.13.9
- lttnng-tools: update 2.13.8 -> 2.13.9
- lttnng-ust: upgrade 2.13.4 -> 2.13.5
- makedepend: upgrade 1.0.6 -> 1.0.8
- make: update 4.3 -> 4.4.1
- man-db: update 2.10.2 -> 2.11.2
- man-pages: upgrade 5.13 -> 6.03
- matchbox-config-gtk: Update to latest SRCREV
- matchbox-desktop-2: Update 2.2 -> 2.3
- matchbox-panel-2: Update 2.11 -> 2.12
- matchbox-terminal: Update to latest SRCREV
- matchbox-wm: Update 1.2.2 -> 1.2.3

- mc: update 4.8.28 -> 4.8.29
- mesa: update 22.2.0 -> 23.0.0
- meson: upgrade 0.63.2 -> 1.0.1
- mmc-utils: upgrade to latest revision
- mobile-broadband-provider-info: upgrade 20220725 -> 20221107
- mpfr: upgrade 4.1.0 -> 4.2.0
- mpg123: upgrade 1.30.2 -> 1.31.2
- msmtplib: upgrade 1.8.22 -> 1.8.23
- mtd-utils: upgrade 2.1.4 -> 2.1.5
- mtools: upgrade 4.0.40 -> 4.0.42
- musl-obstack: Update to 1.2.3
- musl: Upgrade to latest master
- nasm: update 2.15.05 -> 2.16.01
- ncurses: upgrade 6.3+20220423 -> 6.4
- netbase: upgrade 6.3 -> 6.4
- newlib: Upgrade 4.2.0 -> 4.3.0
- nghttp2: upgrade 1.49.0 -> 1.52.0
- numactl: upgrade 2.0.15 -> 2.0.16
- opensbi: Upgrade to 1.2 release
- openssh: upgrade 9.0p1 -> 9.3p1
- openssl: Upgrade 3.0.5 -> 3.1.0
- opkg: upgrade to version 0.6.1
- orc: upgrade 0.4.32 -> 0.4.33
- ovmf: upgrade edk2-stable202205 -> edk2-stable202211
- pango: upgrade 1.50.9 -> 1.50.13
- patchelf: upgrade 0.15.0 -> 0.17.2
- pciutils: upgrade 3.8.0 -> 3.9.0
- piglit: upgrade to latest revision
- pinentry: update 1.2.0 -> 1.2.1
- pixman: upgrade 0.40.0 -> 0.42.2
- pkgconf: upgrade 1.9.3 -> 1.9.4
- popt: update 1.18 -> 1.19

- powertop: upgrade 2.14 -> 2.15
- procps: update 3.3.17 -> 4.0.3
- psmisc: upgrade 23.5 -> 23.6
- puzzles: upgrade to latest revision
- python3-alabaster: upgrade 0.7.12 -> 0.7.13
- python3-attrs: upgrade 22.1.0 -> 22.2.0
- python3-babel: upgrade 2.10.3 -> 2.12.1
- python3-bcrypt: upgrade 3.2.2 -> 4.0.1
- python3-certifi: upgrade 2022.9.14 -> 2022.12.7
- python3-chardet: upgrade 5.0.0 -> 5.1.0
- python3-cryptography: upgrade 38.0.3 -> 39.0.4
- python3-cryptography-vectors: upgrade 37.0.4 -> 39.0.2
- python3-cython: upgrade 0.29.32 -> 0.29.33
- python3-dbusmock: update 0.28.4 -> 0.28.7
- python3-dbus: upgrade 1.2.18 -> 1.3.2
- python3-dtschema: upgrade 2022.8.3 -> 2023.1
- python3-flit-core: upgrade 3.7.1 -> 3.8.0
- python3-gitdb: upgrade 4.0.9 -> 4.0.10
- python3-git: upgrade 3.1.27 -> 3.1.31
- python3-hatch-fancy-pypi-readme: upgrade 22.7.0 -> 22.8.0
- python3-hatchling: upgrade 1.9.0 -> 1.13.0
- python3-hatch-vcs: upgrade 0.2.0 -> 0.3.0
- python3-hypothesis: upgrade 6.54.5 -> 6.68.2
- python3-importlib-metadata: upgrade 4.12.0 -> 6.0.0
- python3-iniconfig: upgrade 1.1.1 -> 2.0.0
- python3-installer: update 0.5.1 -> 0.6.0
- python3-iso8601: upgrade 1.0.2 -> 1.1.0
- python3-jsonschema: upgrade 4.9.1 -> 4.17.3
- python3-lxml: upgrade 4.9.1 -> 4.9.2
- python3-mako: upgrade 1.2.2 -> 1.2.4
- python3-markupsafe: upgrade 2.1.1 -> 2.1.2
- python3-more-itertools: upgrade 8.14.0 -> 9.1.0

- python3-numpy: upgrade 1.23.3 -> 1.24.2
- python3-packaging: upgrade to 23.0
- python3-pathspect: upgrade 0.10.1 -> 0.11.0
- python3-pbr: upgrade 5.10.0 -> 5.11.1
- python3-pip: upgrade 22.2.2 -> 23.0.1
- python3-poetry-core: upgrade 1.0.8 -> 1.5.2
- python3-psutil: upgrade 5.9.2 -> 5.9.4
- python3-pycairo: upgrade 1.21.0 -> 1.23.0
- python3-pycryptodome: upgrade 3.15.0 -> 3.17
- python3-pycryptodomex: upgrade 3.15.0 -> 3.17
- python3-pygments: upgrade 2.13.0 -> 2.14.0
- python3-pyopenssl: upgrade 22.0.0 -> 23.0.0
- python3-pyrsistent: upgrade 0.18.1 -> 0.19.3
- python3-pytest-subtests: upgrade 0.8.0 -> 0.10.0
- python3-pytest: upgrade 7.1.3 -> 7.2.2
- python3-pytz: upgrade 2022.2.1 -> 2022.7.1
- python3-requests: upgrade 2.28.1 -> 2.28.2
- python3-scons: upgrade 4.4.0 -> 4.5.2
- python3-setuptools-rust: upgrade 1.5.1 -> 1.5.2
- python3-setuptools-scm: upgrade 7.0.5 -> 7.1.0
- python3-setuptools: upgrade 65.0.2 -> 67.6.0
- python3-sphinxcontrib-applehelp: update 1.0.2 -> 1.0.4
- python3-sphinxcontrib-htmlhelp: 2.0.0 -> 2.0.1
- python3-sphinx-rtd-theme: upgrade 1.0.0 -> 1.2.0
- python3-sphinx: upgrade 5.1.1 -> 6.1.3
- python3-subunit: upgrade 1.4.0 -> 1.4.2
- python3-testtools: upgrade 2.5.0 -> 2.6.0
- python3-typing-extensions: upgrade 4.3.0 -> 4.5.0
- python3: update 3.10.6 -> 3.11.2
- python3-urllib3: upgrade 1.26.12 -> 1.26.15
- python3-wcwidth: upgrade 0.2.5 -> 0.2.6
- python3-wheel: upgrade 0.37.1 -> 0.40.0

- python3-zipp: upgrade 3.8.1 -> 3.15.0
- qemu: update 7.1.0 -> 7.2.0
- quota: update 4.06 -> 4.09
- readline: update 8.1.2 -> 8.2
- repo: upgrade 2.29.2 -> 2.32
- rgb: update 1.0.6 -> 1.1.0
- rng-tools: upgrade 6.15 -> 6.16
- rsync: update 3.2.5 -> 3.2.7
- rt-tests: update 2.4 -> 2.5
- ruby: update 3.1.2 -> 3.2.1
- rust: update 1.63.0 -> 1.68.1
- rxvt-unicode: upgrade 9.30 -> 9.31
- sed: update 4.8 -> 4.9
- shaderc: upgrade 2022.2 -> 2023.2
- shadow: update 4.12.1 -> 4.13
- socat: upgrade 1.7.4.3 -> 1.7.4.4
- spirv-headers: upgrade 1.3.236.0 -> 1.3.239.0
- spirv-tools: upgrade 1.3.236.0 -> 1.3.239.0
- sqlite3: upgrade 3.39.3 -> 3.41.0
- strace: upgrade 5.19 -> 6.2
- stress-ng: update 0.14.03 -> 0.15.06
- sudo: upgrade 1.9.11p3 -> 1.9.13p3
- swig: update 4.0.2 -> 4.1.1
- sysstat: upgrade 12.6.0 -> 12.6.2
- systemd: update 251.4 -> 253.1
- systemtap: upgrade 4.7 -> 4.8
- taglib: upgrade 1.12 -> 1.13
- tcf-agent: Update to current version
- tcl: update 8.6.11 -> 8.6.13
- texinfo: update 6.8 -> 7.0.2
- tiff: update 4.4.0 -> 4.5.0
- tzdata: update 2022d -> 2023c

- u-boot: upgrade 2022.07 -> 2023.01
- unfs: update 0.9.22 -> 0.10.0
- usbutils: upgrade 014 -> 015
- util-macros: upgrade 1.19.3 -> 1.20.0
- vala: upgrade 0.56.3 -> 0.56.4
- valgrind: update to 3.20.0
- vim: Upgrade 9.0.0598 -> 9.0.1429
- virglrenderer: upgrade 0.10.3 -> 0.10.4
- vte: update 0.68.0 -> 0.72.0
- vulkan-headers: upgrade 1.3.236.0 -> 1.3.239.0
- vulkan-loader: upgrade 1.3.236.0 -> 1.3.239.0
- vulkan-samples: update to latest revision
- vulkan-tools: upgrade 1.3.236.0 -> 1.3.239.0
- vulkan: update 1.3.216.0 -> 1.3.236.0
- wayland-protocols: upgrade 1.26 -> 1.31
- wayland-utils: update 1.0.0 -> 1.1.0
- webkitgtk: update 2.36.7 -> 2.38.5
- weston: update 10.0.2 -> 11.0.1
- wireless-regdb: upgrade 2022.08.12 -> 2023.02.13
- wpebackend-fdo: upgrade 1.12.1 -> 1.14.0
- xcb-util: update 0.4.0 -> 0.4.1
- xcb-util-keysyms: 0.4.0 -> 0.4.1
- xcb-util-renderutil: 0.3.9 -> 0.3.10
- xcb-util-wm: 0.4.1 -> 0.4.2
- xcb-util-image: 0.4.0 -> 0.4.1
- xf86-input-mouse: update 1.9.3 -> 1.9.4
- xf86-input-vmmouse: update 13.1.0 -> 13.2.0
- xf86-video-vesa: update 2.5.0 -> 2.6.0
- xf86-video-vmware: update 13.3.0 -> 13.4.0
- xhost: update 1.0.8 -> 1.0.9
- xinit: update 1.4.1 -> 1.4.2
- xkbcomp: update 1.4.5 -> 1.4.6

- xkeyboard-config: upgrade 2.36 -> 2.38
- xprop: update 1.2.5 -> 1.2.6
- xrandr: upgrade 1.5.1 -> 1.5.2
- xserver-xorg: upgrade 21.1.4 -> 21.1.7
- xset: update 1.2.4 -> 1.2.5
- xvinfo: update 1.1.4 -> 1.1.5
- xwayland: upgrade 22.1.3 -> 22.1.8
- xz: upgrade 5.2.6 -> 5.4.2
- zlib: upgrade 1.2.12 -> 1.2.13
- zstd: upgrade 1.5.2 -> 1.5.4

## Contributors to 4.2

Thanks to the following people who contributed to this release:

- Adrian Freihofer
- Ahmad Fatoum
- Alejandro Hernandez Samaniego
- Alexander Kanavin
- Alexandre Belloni
- Alexey Smirnov
- Alexis Lothoré
- Alex Kiernan
- Alex Stewart
- Andrej Valek
- Andrew Geissler
- Anton Antonov
- Antonin Godard
- Archana Polampalli
- Armin Kuster
- Arnout Vandecappelle
- Arturo Buzarra
- Atanas Bunchev
- Benjamin Szőke
- Benoît Mauduit

- Bernhard Rosenkränzer
- Bruce Ashfield
- Caner Altinbasak
- Carlos Alberto Lopez Perez
- Changhyeok Bae
- Changqing Li
- Charlie Johnston
- Chase Qi
- Chee Yang Lee
- Chen Qi
- Chris Elledge
- Christian Eggers
- Christoph Lauer
- Chuck Wolber
- Ciaran Courtney
- Claus Stovgaard
- Clément Péron
- Daniel Ammann
- David Bagonyi
- Denys Dmytriienko
- Denys Zagorui
- Diego Sueiro
- Dmitry Baryshkov
- Ed Tanous
- Enguerrand de Ribaucourt
- Enrico Jörns
- Enrico Scholz
- Etienne Cordonnier
- Fabio Estevam
- Fabre Sébastien
- Fawzi KHABER
- Federico Pellegrin



- Frank de Brabander
- Frederic Martinsons
- Geoffrey GIRY
- George Kelly
- Harald Seiler
- He Zhe
- Hitendra Prajapati
- Jagadeesh Krishnanjanappa
- James Raphael Tiovalen
- Jan Kircher
- Jan Luebbe
- Jan-Simon Moeller
- Javier Tia
- Jeremy Puhlman
- Jermain Horsman
- Jialing Zhang
- Joel Stanley
- Joe Slater
- Johan Korsnes
- Jon Mason
- Jordan Crouse
- Jose Quaresma
- Joshua Watt
- Justin Bronder
- Kai Kang
- Kasper Revsbech
- Keiya Nobuta
- Kenfe-Mickael Laventure
- Kevin Hao
- Khem Raj
- Konrad Weihmann
- Lei Maohui

- Leon Anavi
- Liam Beguin
- Louis Rannou
- Luca Boccassi
- Luca Ceresoli
- Luis Martins
- Maanya Goenka
- Marek Vasut
- Mark Asselstine
- Mark Hatle
- Markus Volk
- Marta Rybczynska
- Martin Jansa
- Martin Larsson
- Mateusz Marciniec
- Mathieu Dubois-Briand
- Mauro Queiros
- Maxim Uvarov
- Michael Halstead
- Michael Opdenacker
- Mike Crowe
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Narpat Mali
- Nathan Rossi
- Niko Mauno
- Ola x Nilsson
- Oliver Lang
- Ovidiu Panait
- Pablo Saavedra
- Patrick Williams

- Paul Eggleton
- Paulo Neves
- Pavel Zhukov
- Pawel Zalewski
- Pedro Baptista
- Peter Bergin
- Peter Kjellerstedt
- Peter Marko
- Petr Kubizňák
- Petr Vorel
- pgowda
- Piotr Łobacz
- Quentin Schulz
- Randy MacLeod
- Ranjitsinh Rathod
- Ravineet Singh
- Ravula Adhitya Siddartha
- Richard Elberger
- Richard Leitner
- Richard Purdie
- Robert Andersson
- Robert Joslyn
- Robert Yang
- Romuald JEANNE
- Ross Burton
- Ryan Eatmon
- Sakib Sajal
- Sandeep Gundlupet Raju
- Saul Wold
- Sean Anderson
- Sergei Zhmylev
- Siddharth Doshi

- Soumya
- Sudip Mukherjee
- Sundeep KOKKONDA
- Teoh Jay Shen
- Thomas De Schampheleire
- Thomas Perrot
- Thomas Roos
- Tim Orling
- Tobias Hagelborn
- Tom Hochstein
- Trevor Woerner
- Ulrich Ölmann
- Vincent Davis Jr
- Vivek Kumbhar
- Vyacheslav Yurkov
- Wang Mingyu
- Wentao Zhang
- Xiangyu Chen
- Xiaotian Wu
- Yan Xinkuan
- Yash Shinde
- Yi Zhao
- Yoann Congal
- Yureka Lilian
- Zang Ruochen
- Zheng Qiu
- Zheng Ruoqin
- Zoltan Boszormenyi
- 张忠山

## Repositories / Downloads for Yocto-4.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `mickledore`
- Tag: `yocto-4.2`
- Git Revision: `21790e71d55f417f27cd51fae9dd47549758d4a0`
- Release Artefact: `poky-21790e71d55f417f27cd51fae9dd47549758d4a0`
- sha: `38606076765d912deec84e523403709ef1249122197e61454ae08818e60f83c2`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2/poky-21790e71d55f417f27cd51fae9dd47549758d4a0.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.2/poky-21790e71d55f417f27cd51fae9dd47549758d4a0.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `mickledore`
- Tag: `yocto-4.2`
- Git Revision: `c57d1a561db563ed2f521bbac5fc12d4ac8e11a7`
- Release Artefact: `oecore-c57d1a561db563ed2f521bbac5fc12d4ac8e11a7`
- sha: `e8cdd870492017be7e7b74b8c2fb73ae6771b2d2125b2aa1f0e65d0689f96af8`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2/oecore-c57d1a561db563ed2f521bbac5fc12d4ac8e11a7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.2/oecore-c57d1a561db563ed2f521bbac5fc12d4ac8e11a7.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `mickledore`
- Tag: `yocto-4.2`
- Git Revision: `250617ffa524c082b848487359b9d045703d59c2`
- Release Artefact: `meta-mingw-250617ffa524c082b848487359b9d045703d59c2`
- sha: `873a97dfd5ed6fb26e1f6a2ddc2c0c9d7a7b3c7f5018588e912294618775c323`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2/meta-mingw-250617ffa524c082b848487359b9d045703d59c2.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.2/meta-mingw-250617ffa524c082b848487359b9d045703d59c2.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.4`

- Tag: `yocto-4.2`
- Git Revision: `d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c`
- Release Artefact: `bitbake-d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c`
- sha: `5edcb97cb545011226b778355bb840ebcc790552d4a885a0d83178153697ba7a`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2/bitbake-d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2/bitbake-d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `mickledore`
- Tag: `yocto-4.2`
- Git Revision: `4d6807e34adf5d92d9b6e5852736443a867c78fa`

### 17.9.3 Release notes for Yocto-4.2.1 (Mickledore)

#### Security Fixes in Yocto-4.2.1

- connman: Fix [CVE-2023-28488](#)
- linux-yocto: Ignore [CVE-2023-1652](#) and [CVE-2023-1829](#)
- ghostscript: Fix [CVE-2023-28879](#)
- qemu: Ignore [CVE-2023-0664](#)
- ruby: Fix [CVE-2022-28738](#) and [CVE-2022-28739](#)
- tiff: Fix [CVE-2022-4645](#)
- xwayland: Fix [CVE-2023-1393](#)

#### Fixes in Yocto-4.2.1

- apr: upgrade to 1.7.3
- bind: upgrade to 9.18.13
- build-appliance-image: Update to mickledore head revision
- cargo: Fix build on musl/riscv
- cpio: fix appending to archives larger than 2GB
- cracklib: upgrade to 2.9.11
- cve-update-nvd2-native: added the missing http import
- dev-manual: init-manager.rst: add summary
- dhcpcd: use git instead of tarballs
- docs: add support for mickledore (4.2) release

- gawk: Add skipped.txt to emit test to ignore
- gawk: Disable known ptest fails on musl
- gawk: Remove redundant patch
- glib-networking: Add test retry to avoid failures
- glib-networking: Correct glib error handling in test patch
- gtk4: upgrade to 4.10.3
- kernel-devsrc: depend on python3-core instead of python3
- kernel-fitimage: Fix the default dtb config check
- kernel: improve initramfs bundle processing time
- libarchive: Enable acls, xattr for native as well as target
- libhandy: upgrade to 1.8.2
- libnotify: remove dependency dbus
- libpam: Fix the xtests/tst-pam\_motd[1|3] failures
- libpcap: upgrade to 1.10.4
- libsdl2: upgrade to 2.26.5
- libxml2: Disable icu tests on musl
- license.bbclass: Include *LICENSE* in the output when it fails to parse
- linux-firmware: upgrade to 20230404
- machine/qemuarm\*: don't explicitly set vmalloc
- maintainers.inc: Fix email address typo
- maintainers.inc: Move repo to unassigned
- man-pages: upgrade to 6.04
- manuals: document *SPDX\_CUSTOM\_ANNOTATION\_VARS*
- manuals: expand init manager documentation
- mesa: upgrade to 23.0.3
- migration-guides: add release-notes for 4.1.4
- migration-guides: fixes and improvements to 4.2 release notes
- migration-guides: release-notes-4.0.9.rst: add missing *SPDX* info
- migration-guides: release-notes-4.2: add doc improvement highlights
- mpg123: upgrade to 1.31.3
- mtools: upgrade to 4.0.43
- oeqa/utis/metadata.py: Fix running oe-selftest running with no distro set

- overview-manual: development-environment: update text and screenshots
- overview-manual: update section about source archives
- package\_manager/ipk: fix config path generation in `_create_custom_config()`
- pango: upgrade to 1.50.14
- perl: patch out build paths from native binaries
- poky.conf: bump version for 4.2.1 release
- populate\_sdk\_ext.bbclass: redirect stderr to stdout so that both end in LOGFILE
- populate\_sdk\_ext.bbclass: set `METADATA_REVISION` with an `DISTRO` override
- python3targetconfig.bbclass: Extend PYTHONPATH instead of overwriting
- qemu: Add fix for powerpc instruction fallback issue
- qemu: Update ppc instruction fix to match revised upstream version
- quilt: Fix merge.test race condition
- recipes: Default to https git protocol where possible
- ref-manual: add "Mixin" term
- ref-manual: classes.rst: document devicetree.bbclass
- ref-manual: classes: kernel: document automatic defconfig usage
- ref-manual: classes: kernel: remove incorrect sentence opening
- ref-manual: remove unused and obsolete file
- ref-manual: system-requirements.rst: fix AlmaLinux variable name
- ref-manual: variables.rst: add wikipedia shortcut for "getty"
- ref-manual: variables.rst: document `KERNEL_DANGLING_FEATURES_WARN_ONLY`
- ref-manual: variables.rst: don't mention the `INIT_MANAGER` "none" option
- release-notes-4.2: remove/merge duplicates entries
- release-notes-4.2: update RC3 changes
- release-notes-4.2: update known issues and Repositories/Downloads
- releases.svg: fix and explain duration of Hardknott 3.3
- ruby: upgrade to 3.2.2
- rust: upgrade to 1.68.2
- selftest/distrodata: clean up exception lists in recipe maintainers test
- systemd-systemctl: fix instance template WantedBy symlink construction
- texinfo: upgrade to 7.0.3
- unfs3: fix symlink time setting issue



- update-alternatives.bbclass: fix old override syntax
- vala: upgrade to 0.56.6
- waffle: upgrade to 1.7.2
- weston: add xwayland to *DEPENDS* for *PACKAGECONFIG* xwayland
- wpebackend-fdo: upgrade to 1.14.2
- xserver-xorg: upgrade to 21.1.8
- xwayland: upgrade to 23.1.1

### Known Issues in Yocto-4.2.1

- N/A

### Contributors to Yocto-4.2.1

- Alex Kiernan
- Alexander Kanavin
- Arslan Ahmad
- Bruce Ashfield
- Chen Qi
- Dmitry Baryshkov
- Enrico Jörns
- Jan Vermaete
- Joe Slater
- Johannes Schrimpf
- Kai Kang
- Khem Raj
- Kyle Russell
- Lee Chee Yang
- Luca Ceresoli
- Markus Volk
- Martin Jansa
- Martin Siegumfeldt
- Michael Halstead
- Michael Opdenacker
- Ming Liu
- Otavio Salvador

- Pawan Badganchi
- Peter Bergin
- Peter Kjellerstedt
- Piotr Łobacz
- Richard Purdie
- Ross Burton
- Steve Sakoman
- Thomas Roos
- Virendra Thakur
- Wang Mingyu
- Yoann Congal
- Zhixiong Chi

## Repositories / Downloads for Yocto-4.2.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `mickledore`
- Tag: `yocto-4.2.1`
- Git Revision: `c5c69f78fc7ce4ba361363c14352e4264ce7813f`
- Release Artefact: `poky-c5c69f78fc7ce4ba361363c14352e4264ce7813f`
- sha: `057d7771dceebb949a79359d7d028a733a29ae7ecd98b60fefcff83fecb22eb7`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.1/poky-c5c69f78fc7ce4ba361363c14352e4264ce7813f.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.1/poky-c5c69f78fc7ce4ba361363c14352e4264ce7813f.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `mickledore`
- Tag: `yocto-4.2.1`
- Git Revision: `20cd64812d286c920bd766145ab1cd968e72667e`
- Release Artefact: `oecore-20cd64812d286c920bd766145ab1cd968e72667e`
- sha: `877fb909af7aa51e1c962d33cfe91ba3e075c384716006aa1345b4bcb15a48ef`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.1/oecore-20cd64812d286c920bd766145ab1cd968e72667e.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.1/oecore-20cd64812d286c920bd766145ab1cd968e72667e.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: mickledore
- Tag: yocto-4.2.1
- Git Revision: cc9fd0a988dc1041035a6a6cafb2d1237ef38d8e
- Release Artefact: meta-mingw-cc9fd0a988dc1041035a6a6cafb2d1237ef38d8e
- sha: 69ccc3ee503b5c35602889e85d28df64a5422ad0f1e55c96c94135b837bb4a1c
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.1/meta-mingw-cc9fd0a988dc1041035a6a6cafb2d1237ef38d8e.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.1/meta-mingw-cc9fd0a988dc1041035a6a6cafb2d1237ef38d8e.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.4
- Tag: yocto-4.2.1
- Git Revision: d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c
- Release Artefact: bitbake-d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c
- sha: 5edeb97cb545011226b778355bb840ebcc790552d4a885a0d83178153697ba7a
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.1/bitbake-d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.1/bitbake-d97d62e2cbe4bae17f0886f3b4759e8f9ba6d38c.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: mickledore
- Tag: yocto-4.2.1
- Git Revision: 6b04269bba72311e83139cc88b7a3539a5d832e8

## 17.9.4 Release notes for Yocto-4.2.2 (Mickledore)

### Security Fixes in Yocto-4.2.2

- binutils: Fix CVE-2023-1972
- cups: Fix CVE-2023-32324
- curl: Fix CVE-2023-28319, CVE-2023-28320, CVE-2023-28321 and CVE-2023-28322
- dbus: Fix CVE-2023-34969
- git: Fix CVE-2023-25652 and CVE-2023-29007
- git: Ignore CVE-2023-25815

- libwebp: Fix [CVE-2023-1999](#)
- libxml2: Fix [CVE-2023-28484](#) and [CVE-2023-29469](#)
- libxpm: Fix [CVE-2022-44617](#)
- ninja: Ignore [CVE-2021-4336](#)
- openssl: Fix [CVE-2023-0464](#), [CVE-2023-0465](#), [CVE-2023-0466](#), [CVE-2023-1255](#) and [CVE-2023-2650](#)
- perl: Fix [CVE-2023-31484](#) and [CVE-2023-31486](#)
- sysstat: Fix [CVE-2023-33204](#)
- tiff: Fix [CVE-2023-25434](#), [CVE-2023-26965](#) and [CVE-2023-2731](#)
- vim: Fix [CVE-2023-2426](#)

### Fixes in Yocto-4.2.2

- apr: Upgrade to 1.7.4
- avahi: fix D-Bus introspection
- babeltrace2: Always use BFD linker when building tests with ld-is-ld distro feature
- babeltrace2: Upgrade to 2.0.5
- baremetal-helloworld: Update [SRCREV](#) to fix entry addresses for ARM architectures
- bind: Upgrade to 9.18.15
- binutils: move packaging of gprofng static lib into common .inc
- binutils: package static libs from gprofng
- binutils: stable 2.40 branch updates (7343182dd1)
- bitbake.conf: add unzstd in [HOSTTOOLS](#)
- bitbake: runqueue: Fix deferred task/multiconfig race issue
- bno\_plot.py, btt\_plot.py: Ask for python3 specifically
- build-appliance-image: Update to mickledore head revision
- busybox: Upgrade to 1.36.1
- cmake.bbclass: do not search host paths for find\_program()
- conf: add nice level to the hash config ignored variables
- connman: fix warning by specifying runstatedir at configure time
- cpio: Run ptests under ptest user
- dbus: Upgrade to 1.14.8
- devtool: Fix the wrong variable in srcuri\_entry
- dnf: only write the log lock to root for native dnf
- docs: bsp-guide: bsp: fix typo

- dpkg: Upgrade to v1.21.22
- e2fsprogs: Fix error SRCDIR when using usrmerge *DISTRO\_FEATURES*
- e2fsprogs: fix ptest bug for second running
- ell: Upgrade to 0.57
- expect: Add ptest support
- fribidi: Upgrade to 1.0.13
- gawk: Upgrade to 5.2.2
- gcc : upgrade to v12.3
- gdb: fix crashes when debugging threads with Arm Pointer Authentication enabled
- gdb: Upgrade to 13.2
- git: Upgrade to 2.39.3
- glib-networking: use correct error code in ptest
- glibc: Pass linker choice via compiler flags
- glibc: stable 2.37 branch updates.
- gnupg: Upgrade to 2.4.2
- go.bbclass: don't use test to check output from ls
- go: Upgrade to 1.20.5
- go: Use -no-pie to build target cgo
- gobject-introspection: remove obsolete *DEPENDS*
- grub: submit determinism.patch upstream
- gstreamer1.0: Upgrade to 1.22.3
- gtk4: Upgrade to 4.10.4
- image-live.bbclass: respect *IMAGE\_MACHINE\_SUFFIX*
- image\_types: Fix reproducible builds for initramfs and UKI img
- inetutils: remove unused patch files
- ipk: Revert Decode byte data to string in manifest handling
- iso-codes: Upgrade to 4.15.0
- kernel: don't force PAHOLE=false
- kmod: remove unused ptest.patch
- kmscube: Correct *DEPENDS* to avoid overwrite
- layer.conf: Add missing dependency exclusion
- lib/terminal.py: Add urxvt terminal

- libbsd: Add correct license for all packages
- libdnf: Upgrade to 0.70.1
- libgcrypt: Upgrade to 1.10.2
- libgloss: remove unused patch file
- libmicrohttpd: Upgrade to 0.9.77
- libmodule-build-perl: Upgrade to 0.4234
- libx11: remove unused patch and *FILESEXTRAPATHS*
- libx11: Upgrade to 1.8.5
- libxfixes: Upgrade to v6.0.1
- libxft: Upgrade to 2.3.8
- libxi: Upgrade to v1.8.1
- libxml2: Do not use lld linker when building with tests on rv64
- libxml2: Upgrade to 2.10.4
- libxpm: Upgrade to 3.5.16
- linux-firmware: Upgrade to 20230515
- linux-yocto/5.15: cfg: fix DECNET configuration warning
- linux-yocto/5.15: Upgrade to v5.15.118
- linux-yocto/6.1: fix intermittent x86 boot hangs
- linux-yocto/6.1: Upgrade to v6.1.35
- linux-yocto: move build / debug dependencies to .inc
- logrotate: Do not create logrotate.status file
- maintainers.inc: correct Carlos Rafael Giani's email address
- maintainers.inc: correct unassigned entries
- maintainers.inc: unassign Adrian Bunk from wireless-regdb
- maintainers.inc: unassign Alistair Francis from opensbi
- maintainers.inc: unassign Andreas Müller from itstool entry
- maintainers.inc: unassign Chase Qi from libc-test
- maintainers.inc: unassign Oleksandr Kravchuk from python3 and all other items
- maintainers.inc: unassign Pascal Bach from cmake entry
- maintainers.inc: unassign Ricardo Neri from ovmf
- maintainers.inc: update version for gcc-source
- maintainers.inc: unassign Richard Weinberger from erofs-utils entry

- meta: depend on autoconf-archive-native, not autoconf-archive
- meta: lib: oe: npm\_registry: Add more safe characters
- migration-guides: add release notes for 4.2.1
- minicom: remove unused patch files
- mobile-broadband-provider-info: Upgrade to 20230416
- musl: Correct *SRC\_URI*
- oeqa/selftest/bbtests: add non-existent prefile/postfile tests
- oeqa/selftest/cases/devtool.py: skip all tests require folder a git repo
- oeqa: adding selftest-hello and use it to speed up tests
- openssh: Remove BSD-4-clause contents completely from codebase
- openssl: fix building on riscv32
- openssl: Upgrade to 3.1.1
- overview-manual: concepts.rst: Fix a typo
- parted: Add missing libuuid to linker cmdline for libparted-fs-resize.so
- perf: Make built-in libtraceevent plugins cohabit with external libtraceevent
- piglit: Add missing glslang dependencies
- piglit: Fix c++11-narrowing warnings in tests
- pkgconf: Upgrade to 1.9.5
- pm-utils: fix multilib conflixtions
- poky.conf: bump version for 4.2.2 release
- populate\_sdk\_base.bbclass: respect *MLPREFIX* for ptest-pkgs's ptest-runner
- profile-manual: fix blktrace remote usage instructions
- psmisc: Set *ALTERNATIVE* for pstree to resolve conflict with busybox
- ptest-runner: Ensure data writes don't race
- ptest-runner: Pull in "runner: Remove threads and mutexes" fix
- ptest-runner: Pull in sync fix to improve log warnings
- python3-bcrypt: Use BFD linker when building tests
- python3-numpy: remove NPY\_INLINE, use inline instead
- qemu: a pending patch was submitted and accepted upstream
- qemu: remove unused qemu-7.0.0-glibc-2.36.patch
- qemurunner.py: fix error message about qmp
- qemurunner: avoid leaking server\_socket

- ref-manual: add clarification for *SRCREV*
- ref-manual: classes.rst: fix typo
- rootfs-postcommands.bbclass: add post func remove\_unused\_dnf\_log\_lock
- rpcsvc-proto: Upgrade to 1.4.4
- rpm: drop unused 0001-Rip-out-partial-support-for-unused-MD2-and-RIPEMD160.patch
- rpm: Upgrade to 4.18.1
- rpm: write macros under libdir
- runqemu-gen-tapdevs: Refactoring
- runqemu-ifupdown/get-tapdevs: Add support for ip tuntap
- scripts/runqemu: allocate unfsd ports in a way that doesn't race or clash with unrelated processes
- scripts/runqemu: split lock dir creation into a reusable function
- scripts: fix buildstats diff/summary hard bound to host python3
- sdk.py: error out when moving file fails
- sdk.py: fix moving dnf contents
- selftest/license: Exclude from world
- selftest/reproducible: Allow native/cross reuse in test
- serf: Upgrade to 1.3.10
- staging.bbclass: do not add extend\_recipe\_sysroot to prefuns of prepare\_recipe\_sysroot
- strace: Disable failing test
- strace: Merge two similar patches
- strace: Update patches/tests with upstream fixes
- sysfsutils: fetch a supported fork from github
- systemd-systemctl: support instance expansion in WantedBy
- systemd: Drop a backport
- tiff: Remove unused patch from tiff
- uninative: Upgrade to 3.10 to support gcc 13
- uninative: Upgrade to 4.0 to include latest gcc 13.1.1
- unzip: fix configure check for cross compilation
- unzip: remove hardcoded LARGE\_FILE\_SUPPORT
- useradd-example: package typo correction
- useradd-staticids.bbclass: improve error message
- v86d: Improve kernel dependency



- vim: Upgrade to 9.0.1527
- weston-init: add profile to point users to global socket
- weston-init: add the weston user to the wayland group
- weston-init: add weston user to the render group
- weston-init: fix the mixed indentation
- weston-init: guard against systemd configs
- weston-init: make sure the render group exists
- wget: Upgrade to 1.21.4
- wireless-regdb: Upgrade to 2023.05.03
- xdpinfo: Upgrade to 1.3.4
- xf86-video-intel: Use the HTTPS protocol to fetch the Git repositories
- xinput: upgrade to v1.6.4
- xwininfo: upgrade to v1.1.6
- xz: Upgrade to 5.4.3
- yocto-bsps: update to v5.15.106
- zip: fix configure check by using `_Static_assert`
- zip: remove unnecessary `LARGE_FILE_SUPPORT` CLFAGS

### Known Issues in Yocto-4.2.2

- N/A

### Contributors to Yocto-4.2.2

- Alberto Planas
- Alejandro Hernandez Samaniego
- Alexander Kanavin
- Andrej Valek
- Andrew Jeffery
- Anuj Mittal
- Archana Polampalli
- BELOUARGA Mohamed
- Bruce Ashfield
- Changqing Li
- Charlie Wu
- Chen Qi

- Chi Xu
- Daniel Ammann
- Deepthi Hemraj
- Denys Dmytriienko
- Dmitry Baryshkov
- Ed Beroet
- Eero Aaltonen
- Fabien Mahot
- Frieder Paape
- Frieder Schrempf
- Hannu Lounento
- Ian Ray
- Jermain Horsman
- Jörg Sommer
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Lorenzo Arena
- Marc Ferland
- Markus Volk
- Martin Jansa
- Michael Halstead
- Mikko Rapeli
- Mingli Yu
- Natasha Bailey
- Nikhil R
- Pablo Saavedra
- Paul Gortmaker
- Pavel Zhukov
- Peter Kjellerstedt
- Qiu Tingting
- Quentin Schulz

- Randolph Sapp
- Randy MacLeod
- Ranjitsinh Rathod
- Richard Purdie
- Riyaz Khan
- Ross Burton
- Sakib Sajal
- Sanjay Chitroda
- Siddharth Doshi
- Soumya Sambu
- Steve Sakoman
- Sudip Mukherjee
- Sundeep KOKKONDA
- Thomas Roos
- Tim Orling
- Tom Hochstein
- Trevor Gamblin
- Ulrich Ölmann
- Wang Mingyu
- Xiangyu Chen

## Repositories / Downloads for Yocto-4.2.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [mickledore](#)
- Tag: [yocto-4.2.2](#)
- Git Revision: [6e17b3e644ca15b8b4afd071ccaa6f172a0e681a](#)
- Release Artefact: [poky-6e17b3e644ca15b8b4afd071ccaa6f172a0e681a](#)
- sha: [c0b4dadcf00b97d866dd4cc2f162474da2c3e3289badaa42a978bff1d479af99](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.2/poky-6e17b3e644ca15b8b4afd071ccaa6f172a0e681a.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.2/poky-6e17b3e644ca15b8b4afd071ccaa6f172a0e681a.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>

- Branch: `mickledore`
- Tag: `yocto-4.2.2`
- Git Revision: `3ef283e02b0b91daf64c3a589e1f6bb68d4f5aa1`
- Release Artefact: `oecore-3ef283e02b0b91daf64c3a589e1f6bb68d4f5aa1`
- sha: `d2fd127f46e626fa4456c193af3dbd25d4b2565db59bc23be69a3b2dd4febed5`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.2/oecore-3ef283e02b0b91daf64c3a589e1f6bb68d4f5aa1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.2/oecore-3ef283e02b0b91daf64c3a589e1f6bb68d4f5aa1.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `mickledore`
- Tag: `yocto-4.2.2`
- Git Revision: `4608d0bb7e47c52b8f6e9be259bfb1716fda9fd6`
- Release Artefact: `meta-mingw-4608d0bb7e47c52b8f6e9be259bfb1716fda9fd6`
- sha: `fcbae0dedb363477492b86b8f997e06f995793285535b24dc66038845483eeef`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.2/meta-mingw-4608d0bb7e47c52b8f6e9be259bfb1716fda9fd6.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.2/meta-mingw-4608d0bb7e47c52b8f6e9be259bfb1716fda9fd6.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.4`
- Tag: `yocto-4.2.2`
- Git Revision: `08033b63ae442c774bd3fce62844eac23e6882d7`
- Release Artefact: `bitbake-08033b63ae442c774bd3fce62844eac23e6882d7`
- sha: `1d070c133bfb6502ac04befbf082cbfda7582c8b1c48296a788384352e5061fd`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.2/bitbake-08033b63ae442c774bd3fce62844eac23e6882d7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.2/bitbake-08033b63ae442c774bd3fce62844eac23e6882d7.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `mickledore`
- Tag: `yocto-4.2.2`
- Git Revision: `54d849d259a332389beea159d789f8fa92871475`

## 17.9.5 Release notes for Yocto-4.2.3 (Mickledore)

### Security Fixes in Yocto-4.2.3

- bind: Fix [CVE-2023-2828](#) and [CVE-2023-2911](#)
- cups: Fix [CVE-2023-34241](#)
- dmidecode: Fix [CVE-2023-30630](#)
- erofs-utils: Fix [CVE-2023-33551](#) and [CVE-2023-33552](#)
- ghostscript: Fix [CVE-2023-36664](#)
- go: Fix [CVE-2023-24531](#)
- libarchive: ignore [CVE-2023-30571](#)
- libjpeg-turbo: Fix [CVE-2023-2804](#)
- libx11: Fix [CVE-2023-3138](#)
- ncurses: Fix [CVE-2023-29491](#)
- openssh: Fix [CVE-2023-38408](#)
- python3-certifi: Fix [CVE-2023-37920](#)
- python3-requests: Fix [CVE-2023-32681](#)
- python3: Ignore [CVE-2023-36632](#)
- qemu: fix [CVE-2023-0330](#), [CVE-2023-2861](#), [CVE-2023-3255](#) and [CVE-2023-3301](#)
- ruby: Fix [CVE-2023-36617](#)
- vim: Fix [CVE-2023-2609](#) and [CVE-2023-2610](#)
- webkitgtk: Fix [CVE-2023-27932](#) and [CVE-2023-27954](#)

### Fixes in Yocto-4.2.3

- acpica: Update *SRC\_URI*
- automake: fix buildtest patch
- baremetal-helloworld: Fix race condition
- bind: upgrade to v9.18.17
- binutils: stable 2.40 branch updates
- build-appliance-image: Update to mickledore head revision
- cargo.bbclass: set up cargo environment in common do\_compile
- conf.py: add macro for Mitre CVE links
- curl: ensure all ptest failures are caught
- cve-update-nvd2-native: actually use API keys
- cve-update-nvd2-native: fix cvssV3 metrics

- cve-update-nvd2-native: handle all configuration nodes, not just first
- cve-update-nvd2-native: increase retry count
- cve-update-nvd2-native: log a little more
- cve-update-nvd2-native: retry all errors and sleep between retries
- cve-update-nvd2-native: use exact times, don't truncate
- dev-manual: wic.rst: Update native tools build command
- devtool/upgrade: raise an error if extracting source produces more than one directory
- diffutils: upgrade to 3.10
- docs: ref-manual: terms: fix typos in *SPDX* term
- file: fix the way path is written to environment-setup.d
- file: return wrapper to fix builds when file is in buildtools-tarball
- freetype: upgrade to 2.13.1
- gcc-testsuite: Fix ppc cpu specification
- gcc: don't pass --enable-standard-branch-protection
- glibc-locale: use stricter matching for metapackages' runtime dependencies
- glibc-testsuite: Fix network restrictions causing test failures
- glibc/check-test-wrapper: don't emit warnings from ssh
- go: upgrade to 1.20.6
- gstreamer1.0: upgrade to 1.22.4
- ifupdown: install missing directories
- kernel-module-split add systemd modulesloadir and modprobedir config
- kernel-module-split: install config modules directories only when they are needed
- kernel-module-split: make autoload and probeconf distribution specific
- kernel-module-split: use context manager to open files
- kernel: Fix path comparison in kernel staging dir symlinking
- kernel: config modules directories are handled by kernel-module-split
- kernel: don't fail if Modules.symvers doesn't exist
- libassuan: upgrade to 2.5.6
- libksba: upgrade to 1.6.4
- libnss-nis: upgrade to 3.2
- libproxy: fetch from git
- libwebp: upgrade to 1.3.1

- libx11: upgrade to 1.8.6
- libxcrypt: fix hard-coded ".so" extension
- linux-firmware : Add firmware of RTL8822 serie
- linux-firmware: Fix mediatek mt7601u firmware path
- linux-firmware: package firmare for Dragonboard 410c
- linux-firmware: split platform-specific Adreno shaders to separate packages
- linux-firmware: upgrade to 20230625
- linux-yocto/5.15: update to v5.15.124
- linux-yocto/6.1: cfg: update ima.cfg to match current meta-integrity
- linux-yocto/6.1: upgrade to v6.1.38
- ltp: Add kernel loopback module dependency
- ltp: add *RDEPENDS* on findutils
- ltng-ust: upgrade to 2.13.6
- machine/arch-arm64: add -mbranch-protection=standard
- maintainers.inc: Modify email address
- mdadm: add util-linux-blockdev ptest dependency
- mdadm: fix 07revert-inplace ptest
- mdadm: fix segfaults when running ptests
- mdadm: fix util-linux ptest dependency
- mdadm: re-add mdadm-ptest to PTESTS\_SLOW
- mdadm: skip running known broken ptests
- meson.bbclass: Point to llvm-config from native sysroot
- migration-guides: add release notes for 4.0.10
- migration-guides: add release notes for 4.0.11
- migration-guides: add release notes for 4.2.2
- oeqa/runtime/cases/rpm: fix wait\_for\_no\_process\_for\_user failure case
- oeqa/runtime/ltp: Increase ltp test output timeout
- oeqa/selftest/devtool: add unit test for "devtool add -b"
- oeqa/ssh: Further improve process exit handling
- oeqa/target/ssh: Ensure EAGAIN doesn't truncate output
- oeqa/utls/nfs: allow requesting non-udp ports
- openssh: upgrade to 9.3p2

- openssl: add PERLEXTERNAL path to test its existence
- openssl: use a glob on the PERLEXTERNAL to track updates on the path
- opkg-utils: upgrade to 0.6.2
- opkg: upgrade to 0.6.2
- pkgconf: update *SRC\_URI*
- poky.conf: bump version for 4.2.3 release
- poky.conf: update *SANITY\_TESTED\_DISTROS* to match autobuilder
- ptest-runner: Pull in parallel test fixes and output handling
- python3-certifi: upgrade to 2023.7.22
- python3: fix missing comma in get\_module\_deps3.py
- recipetool: Fix inherit in created -native\* recipes
- ref-manual: LTS releases now supported for 4 years
- ref-manual: document image-specific variant of *INCOMPATIBLE\_LICENSE*
- ref-manual: releases.svg: updates
- resulttool/resultutils: allow index generation despite corrupt json
- rootfs-postcommands.bbclass: Revert "add post func remove\_unused\_dnf\_log\_lock"
- rootfs: Add debugfs package db file copy and cleanup
- rootfs\_rpm: don't depend on opkg-native for update-alternatives
- rpm: Pick debugfs package db files/dirs explicitly
- rust-common.bbclass: move musl-specific linking fix from rust-source.inc
- scripts/oe-setup-builddir: copy conf-notes.txt to build dir
- scripts/resulttool: add mention about new detected tests
- selftest/cases/glibc.py: fix the override syntax
- selftest/cases/glibc.py: increase the memory for testing
- selftest/cases/glibc.py: switch to using NFS over TCP
- shadow-sysroot: add license information
- systemd-systemctl: fix errors in instance name expansion
- taglib: upgrade to 1.13.1
- target/ssh: Ensure exit code set for commands
- tcf-agent: upgrade to 1.8.0
- testimage/oeqa: Drop testimage\_dump\_host functionality
- tiff: upgrade to 4.5.1



- uboot-extlinux-config.bbclass: fix old override syntax in comment
- util-linux: add alternative links for ipcs,ipcrm
- vim: upgrade to 9.0.1592
- webkitgtk: upgrade to 2.38.6
- weston: Cleanup and fix x11 and xwayland dependencies

### Known Issues in Yocto-4.2.3

- N/A

### Contributors to Yocto-4.2.3

- Alejandro Hernandez Samaniego
- Alex Kiernan
- Alexander Kanavin
- Alexis Lothoré
- Andrej Valek
- Anuj Mittal
- Archana Polampalli
- BELOUARGA Mohamed
- Benjamin Bouvier
- Bruce Ashfield
- Changqing Li
- Chen Qi
- Daniel Semkowicz
- Dmitry Baryshkov
- Enrico Scholz
- Etienne Cordonnier
- Joe Slater
- Joel Stanley
- Jose Quaresma
- Julien Stephan
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Marek Vasut

- Mark Hatle
- Michael Halstead
- Michael Opdenacker
- Mingli Yu
- Narpat Mali
- Oleksandr Hnatiuk
- Ovidiu Panait
- Peter Marko
- Quentin Schulz
- Richard Purdie
- Ross Burton
- Sanjana
- Sakib Sajal
- Staffan Rydén
- Steve Sakoman
- Stéphane Veyret
- Sudip Mukherjee
- Thomas Roos
- Tom Hochstein
- Trevor Gamblin
- Wang Mingyu
- Yi Zhao
- Yoann Congal
- Yogita Urade
- Yuta Hayama

### **Repositories / Downloads for Yocto-4.2.3**

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [mickledore](#)
- Tag: [yocto-4.2.3](#)
- Git Revision: [aa63b25cbe25d89ab07ca11ee72c17cab68df8de](#)
- Release Artefact: [poky-aa63b25cbe25d89ab07ca11ee72c17cab68df8de](#)

- sha: 9e2b40fc25f7984b3227126ec9b8aa68d3747c8821fb7bf8cb635fc143f894c3
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.3/poky-aa63b25cbe25d89ab07ca11ee72c17cab68df8de.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.3/poky-aa63b25cbe25d89ab07ca11ee72c17cab68df8de.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: mickledore
- Tag: yocto-4.2.3
- Git Revision: 7e3489c0c5970389c8a239dc7b367bcadf554eb5
- Release Artefact: oecore-7e3489c0c5970389c8a239dc7b367bcadf554eb5
- sha: 68620aca7c9db6b9a65d9853cacff4e60578f0df39e3e37114e062e1667ba724
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.3/oecore-7e3489c0c5970389c8a239dc7b367bcadf554eb5.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.3/oecore-7e3489c0c5970389c8a239dc7b367bcadf554eb5.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: mickledore
- Tag: yocto-4.2.3
- Git Revision: 92258028e1b5664a9f832541d5c4f6de0bd05e07
- Release Artefact: meta-mingw-92258028e1b5664a9f832541d5c4f6de0bd05e07
- sha: ee081460b5dff4fb8dd4869ce5631718dbaaffbede9532b879b854c18f1b3f5d
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.3/meta-mingw-92258028e1b5664a9f832541d5c4f6de0bd05e07.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.3/meta-mingw-92258028e1b5664a9f832541d5c4f6de0bd05e07.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.4
- Tag: yocto-4.2.3
- Git Revision: 08033b63ae442c774bd3fce62844eac23e6882d7
- Release Artefact: bitbake-08033b63ae442c774bd3fce62844eac23e6882d7
- sha: 1d070c133bfb6502ac04befbf082cbfda7582c8b1c48296a788384352e5061fd
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.3/bitbake-08033b63ae442c774bd3fce62844eac23e6882d7.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.3/bitbake-08033b63ae442c774bd3fce62844eac23e6882d7.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `mickledore`
- Tag: `yocto-4.2.3`
- Git Revision: `8e6752a9e55d16f3713e248b37f9d4d2745a2375`

## 17.9.6 Release notes for Yocto-4.2.4 (Mickledore)

### Security Fixes in Yocto-4.2.4

- `bind`: Fix CVE-2023-3341 and CVE-2023-4236
- `binutils`: Fix CVE-2023-39128
- `cups`: fix CVE-2023-4504
- `curl`: Fix CVE-2023-28320, CVE-2023-32001, CVE-2023-38039, CVE-2023-38545 and CVE-2023-38546
- `dmidecode`: fix for CVE-2023-30630
- `dropbear`: fix CVE-2023-36328
- `ffmpeg`: Ignore CVE-2023-39018
- `gcc`: Fix CVE-2023-4039
- `gdb`: Fix CVE-2023-39128
- `ghostscript`: Fix CVE-2023-38559 and CVE-2023-43115
- `glibc`: Fix CVE-2023-4527 and CVE-2023-4806
- `go`: Fix CVE-2023-29409 and CVE-2023-39533
- `grub`: Fix CVE-2023-4692 and CVE-2023-4693
- `gststreamer`: Fix CVE-2023-40474, CVE-2023-40475 and CVE-2023-40476
- `inetutils`: fix CVE-2023-40303
- `librsvg`: Fix CVE-2023-38633
- `libssh2`: Fix CVE-2020-22218
- `libwebp`: Fix CVE-2023-4863 and CVE-2023-5129
- `libx11`: Fix CVE-2023-43785, CVE-2023-43786 and CVE-2023-43787
- `libxpm`: Fix CVE-2023-43788 and CVE-2023-43789
- `linux-yocto/6.1`: Ignore CVE-2003-1604, CVE-2004-0230, CVE-2006-3635, CVE-2006-5331, CVE-2006-6128, CVE-2007-4774, CVE-2007-6761, CVE-2007-6762, CVE-2008-7316, CVE-2009-2692, CVE-2010-0008, CVE-2010-3432, CVE-2010-4648, CVE-2010-5313, CVE-2010-5328, CVE-2010-5329, CVE-2010-5331, CVE-2010-5332, CVE-2011-4098, CVE-2011-4131, CVE-2011-4915, CVE-2011-5321, CVE-2011-5327, CVE-2012-0957, CVE-2012-2119, CVE-2012-2136, CVE-2012-2137, CVE-2012-2313, CVE-2012-2319, CVE-2012-2372, CVE-2012-2375, CVE-2012-2390, CVE-2012-2669, CVE-2012-2744, CVE-2012-2745, CVE-2012-3364, CVE-2012-3375, CVE-2012-3400, CVE-2012-3412, CVE-2012-3430, CVE-2012-3510, CVE-2012-3511, CVE-2012-3520, CVE-2012-3552, CVE-2012-4398, CVE-2012-4444, CVE-2012-

4461, CVE-2012-4467, CVE-2012-4508, CVE-2012-4530, CVE-2012-4565, CVE-2012-5374, CVE-2012-5375, CVE-2012-5517, CVE-2012-6536, CVE-2012-6537, CVE-2012-6538, CVE-2012-6539, CVE-2012-6540, CVE-2012-6541, CVE-2012-6542, CVE-2012-6543, CVE-2012-6544, CVE-2012-6545, CVE-2012-6546, CVE-2012-6547, CVE-2012-6548, CVE-2012-6549, CVE-2012-6638, CVE-2012-6647, CVE-2012-6657, CVE-2012-6689, CVE-2012-6701, CVE-2012-6703, CVE-2012-6704, CVE-2012-6712, CVE-2013-0160, CVE-2013-0190, CVE-2013-0216, CVE-2013-0217, CVE-2013-0228, CVE-2013-0231, CVE-2013-0268, CVE-2013-0290, CVE-2013-0309, CVE-2013-0310, CVE-2013-0311, CVE-2013-0313, CVE-2013-0343, CVE-2013-0349, CVE-2013-0871, CVE-2013-0913, CVE-2013-0914, CVE-2013-1059, CVE-2013-1763, CVE-2013-1767, CVE-2013-1772, CVE-2013-1773, CVE-2013-1774, CVE-2013-1792, CVE-2013-1796, CVE-2013-1797, CVE-2013-1798, CVE-2013-1819, CVE-2013-1826, CVE-2013-1827, CVE-2013-1828, CVE-2013-1848, CVE-2013-1858, CVE-2013-1860, CVE-2013-1928, CVE-2013-1929, CVE-2013-1943, CVE-2013-1956, CVE-2013-1957, CVE-2013-1958, CVE-2013-1959, CVE-2013-1979, CVE-2013-2015, CVE-2013-2017, CVE-2013-2058, CVE-2013-2094, CVE-2013-2128, CVE-2013-2140, CVE-2013-2141, CVE-2013-2146, CVE-2013-2147, CVE-2013-2148, CVE-2013-2164, CVE-2013-2206, CVE-2013-2232, CVE-2013-2234, CVE-2013-2237, CVE-2013-2546, CVE-2013-2547, CVE-2013-2548, CVE-2013-2596, CVE-2013-2634, CVE-2013-2635, CVE-2013-2636, CVE-2013-2850, CVE-2013-2851, CVE-2013-2852, CVE-2013-2888, CVE-2013-2889, CVE-2013-2890, CVE-2013-2891, CVE-2013-2892, CVE-2013-2893, CVE-2013-2894, CVE-2013-2895, CVE-2013-2896, CVE-2013-2897, CVE-2013-2898, CVE-2013-2899, CVE-2013-2929, CVE-2013-2930, CVE-2013-3076, CVE-2013-3222, CVE-2013-3223, CVE-2013-3224, CVE-2013-3225, CVE-2013-3226, CVE-2013-3227, CVE-2013-3228, CVE-2013-3229, CVE-2013-3230, CVE-2013-3231, CVE-2013-3232, CVE-2013-3233, CVE-2013-3234, CVE-2013-3235, CVE-2013-3236, CVE-2013-3237, CVE-2013-3301, CVE-2013-3302, CVE-2013-4125, CVE-2013-4127, CVE-2013-4129, CVE-2013-4162, CVE-2013-4163, CVE-2013-4205, CVE-2013-4220, CVE-2013-4247, CVE-2013-4254, CVE-2013-4270, CVE-2013-4299, CVE-2013-4300, CVE-2013-4312, CVE-2013-4343, CVE-2013-4345, CVE-2013-4348, CVE-2013-4350, CVE-2013-4387, CVE-2013-4470, CVE-2013-4483, CVE-2013-4511, CVE-2013-4512, CVE-2013-4513, CVE-2013-4514, CVE-2013-4515, CVE-2013-4516, CVE-2013-4563, CVE-2013-4579, CVE-2013-4587, CVE-2013-4588, CVE-2013-4591, CVE-2013-4592, CVE-2013-5634, CVE-2013-6282, CVE-2013-6367, CVE-2013-6368, CVE-2013-6376, CVE-2013-6378, CVE-2013-6380, CVE-2013-6381, CVE-2013-6382, CVE-2013-6383, CVE-2013-6431, CVE-2013-6432, CVE-2013-6885, CVE-2013-7026, CVE-2013-7027, CVE-2013-7263, CVE-2013-7264, CVE-2013-7265, CVE-2013-7266, CVE-2013-7267, CVE-2013-7268, CVE-2013-7269, CVE-2013-7270, CVE-2013-7271, CVE-2013-7281, CVE-2013-7339, CVE-2013-7348, CVE-2013-7421, CVE-2013-7446, CVE-2013-7470, CVE-2014-0038, CVE-2014-0049, CVE-2014-0055, CVE-2014-0069, CVE-2014-0077, CVE-2014-0100, CVE-2014-0101, CVE-2014-0102, CVE-2014-0131, CVE-2014-0155, CVE-2014-0181, CVE-2014-0196, CVE-2014-0203, CVE-2014-0205, CVE-2014-0206, CVE-2014-1438, CVE-2014-1444, CVE-2014-1445, CVE-2014-1446, CVE-2014-1690, CVE-2014-1737, CVE-2014-1738, CVE-2014-1739, CVE-2014-1874, CVE-2014-2038, CVE-2014-2039, CVE-2014-2309, CVE-2014-2523, CVE-2014-2568, CVE-2014-2580, CVE-2014-2672, CVE-2014-2673, CVE-2014-2678, CVE-2014-2706, CVE-2014-2739, CVE-2014-2851, CVE-2014-2889, CVE-2014-3122, CVE-2014-3144, CVE-2014-3145, CVE-2014-3153, CVE-2014-3180, CVE-2014-3181, CVE-2014-3182, CVE-2014-3183, CVE-2014-3184, CVE-2014-3185, CVE-2014-3186, CVE-2014-3534, CVE-2014-3535, CVE-2014-3601, CVE-2014-3610, CVE-2014-3611, CVE-2014-3631, CVE-2014-3645, CVE-2014-3646, CVE-2014-3647, CVE-2014-3673, CVE-2014-3687, CVE-2014-3688, CVE-2014-3690, CVE-2014-3917, CVE-2014-3940, CVE-2014-4014, CVE-2014-4027, CVE-2014-4157, CVE-2014-4171, CVE-2014-4508, CVE-2014-4608, CVE-2014-4611, CVE-2014-4652, CVE-2014-4653, CVE-2014-4654, CVE-2014-4655, CVE-2014-4656, CVE-2014-4667, CVE-2014-4699, CVE-2014-4943, CVE-2014-

5045, CVE-2014-5077, CVE-2014-5206, CVE-2014-5207, CVE-2014-5471, CVE-2014-5472, CVE-2014-6410, CVE-2014-6416, CVE-2014-6417, CVE-2014-6418, CVE-2014-7145, CVE-2014-7283, CVE-2014-7284, CVE-2014-7822, CVE-2014-7825, CVE-2014-7826, CVE-2014-7841, CVE-2014-7842, CVE-2014-7843, CVE-2014-7970, CVE-2014-7975, CVE-2014-8086, CVE-2014-8133, CVE-2014-8134, CVE-2014-8159, CVE-2014-8160, CVE-2014-8171, CVE-2014-8172, CVE-2014-8173, CVE-2014-8369, CVE-2014-8480, CVE-2014-8481, CVE-2014-8559, CVE-2014-8709, CVE-2014-8884, CVE-2014-8989, CVE-2014-9090, CVE-2014-9322, CVE-2014-9419, CVE-2014-9420, CVE-2014-9428, CVE-2014-9529, CVE-2014-9584, CVE-2014-9585, CVE-2014-9644, CVE-2014-9683, CVE-2014-9710, CVE-2014-9715, CVE-2014-9717, CVE-2014-9728, CVE-2014-9729, CVE-2014-9730, CVE-2014-9731, CVE-2014-9803, CVE-2014-9870, CVE-2014-9888, CVE-2014-9895, CVE-2014-9903, CVE-2014-9904, CVE-2014-9914, CVE-2014-9922, CVE-2014-9940, CVE-2015-0239, CVE-2015-0274, CVE-2015-0275, CVE-2015-1333, CVE-2015-1339, CVE-2015-1350, CVE-2015-1420, CVE-2015-1421, CVE-2015-1465, CVE-2015-1573, CVE-2015-1593, CVE-2015-1805, CVE-2015-2041, CVE-2015-2042, CVE-2015-2150, CVE-2015-2666, CVE-2015-2672, CVE-2015-2686, CVE-2015-2830, CVE-2015-2922, CVE-2015-2925, CVE-2015-3212, CVE-2015-3214, CVE-2015-3288, CVE-2015-3290, CVE-2015-3291, CVE-2015-3331, CVE-2015-3339, CVE-2015-3636, CVE-2015-4001, CVE-2015-4002, CVE-2015-4003, CVE-2015-4004, CVE-2015-4036, CVE-2015-4167, CVE-2015-4170, CVE-2015-4176, CVE-2015-4177, CVE-2015-4178, CVE-2015-4692, CVE-2015-4700, CVE-2015-5156, CVE-2015-5157, CVE-2015-5257, CVE-2015-5283, CVE-2015-5307, CVE-2015-5327, CVE-2015-5364, CVE-2015-5366, CVE-2015-5697, CVE-2015-5706, CVE-2015-5707, CVE-2015-6252, CVE-2015-6526, CVE-2015-6937, CVE-2015-7509, CVE-2015-7513, CVE-2015-7515, CVE-2015-7550, CVE-2015-7566, CVE-2015-7613, CVE-2015-7799, CVE-2015-7833, CVE-2015-7872, CVE-2015-7884, CVE-2015-7885, CVE-2015-7990, CVE-2015-8104, CVE-2015-8215, CVE-2015-8324, CVE-2015-8374, CVE-2015-8539, CVE-2015-8543, CVE-2015-8550, CVE-2015-8551, CVE-2015-8552, CVE-2015-8553, CVE-2015-8569, CVE-2015-8575, CVE-2015-8660, CVE-2015-8709, CVE-2015-8746, CVE-2015-8767, CVE-2015-8785, CVE-2015-8787, CVE-2015-8812, CVE-2015-8816, CVE-2015-8830, CVE-2015-8839, CVE-2015-8844, CVE-2015-8845, CVE-2015-8950, CVE-2015-8952, CVE-2015-8953, CVE-2015-8955, CVE-2015-8956, CVE-2015-8961, CVE-2015-8962, CVE-2015-8963, CVE-2015-8964, CVE-2015-8966, CVE-2015-8967, CVE-2015-8970, CVE-2015-9004, CVE-2015-9016, CVE-2015-9289, CVE-2016-0617, CVE-2016-0723, CVE-2016-0728, CVE-2016-0758, CVE-2016-0821, CVE-2016-0823, CVE-2016-10044, CVE-2016-10088, CVE-2016-10147, CVE-2016-10150, CVE-2016-10153, CVE-2016-10154, CVE-2016-10200, CVE-2016-10208, CVE-2016-10229, CVE-2016-10318, CVE-2016-10723, CVE-2016-10741, CVE-2016-10764, CVE-2016-10905, CVE-2016-10906, CVE-2016-10907, CVE-2016-1237, CVE-2016-1575, CVE-2016-1576, CVE-2016-1583, CVE-2016-2053, CVE-2016-2069, CVE-2016-2070, CVE-2016-2085, CVE-2016-2117, CVE-2016-2143, CVE-2016-2184, CVE-2016-2185, CVE-2016-2186, CVE-2016-2187, CVE-2016-2188, CVE-2016-2383, CVE-2016-2384, CVE-2016-2543, CVE-2016-2544, CVE-2016-2545, CVE-2016-2546, CVE-2016-2547, CVE-2016-2548, CVE-2016-2549, CVE-2016-2550, CVE-2016-2782, CVE-2016-2847, CVE-2016-3044, CVE-2016-3070, CVE-2016-3134, CVE-2016-3135, CVE-2016-3136, CVE-2016-3137, CVE-2016-3138, CVE-2016-3139, CVE-2016-3140, CVE-2016-3156, CVE-2016-3157, CVE-2016-3672, CVE-2016-3689, CVE-2016-3713, CVE-2016-3841, CVE-2016-3857, CVE-2016-3951, CVE-2016-3955, CVE-2016-3961, CVE-2016-4440, CVE-2016-4470, CVE-2016-4482, CVE-2016-4485, CVE-2016-4486, CVE-2016-4557, CVE-2016-4558, CVE-2016-4565, CVE-2016-4568, CVE-2016-4569, CVE-2016-4578, CVE-2016-4580, CVE-2016-4581, CVE-2016-4794, CVE-2016-4805, CVE-2016-4913, CVE-2016-4951, CVE-2016-4997, CVE-2016-4998, CVE-2016-5195, CVE-2016-5243, CVE-2016-5244, CVE-2016-5400, CVE-2016-5412, CVE-2016-5696, CVE-2016-5728, CVE-2016-5828, CVE-2016-5829, CVE-2016-6130, CVE-2016-6136, CVE-2016-6156, CVE-2016-6162, CVE-2016-6187, CVE-

2016-6197, CVE-2016-6198, CVE-2016-6213, CVE-2016-6327, CVE-2016-6480, CVE-2016-6516, CVE-2016-6786, CVE-2016-6787, CVE-2016-6828, CVE-2016-7039, CVE-2016-7042, CVE-2016-7097, CVE-2016-7117, CVE-2016-7425, CVE-2016-7910, CVE-2016-7911, CVE-2016-7912, CVE-2016-7913, CVE-2016-7914, CVE-2016-7915, CVE-2016-7916, CVE-2016-7917, CVE-2016-8399, CVE-2016-8405, CVE-2016-8630, CVE-2016-8632, CVE-2016-8633, CVE-2016-8636, CVE-2016-8645, CVE-2016-8646, CVE-2016-8650, CVE-2016-8655, CVE-2016-8658, CVE-2016-8666, CVE-2016-9083, CVE-2016-9084, CVE-2016-9120, CVE-2016-9178, CVE-2016-9191, CVE-2016-9313, CVE-2016-9555, CVE-2016-9576, CVE-2016-9588, CVE-2016-9604, CVE-2016-9685, CVE-2016-9754, CVE-2016-9755, CVE-2016-9756, CVE-2016-9777, CVE-2016-9793, CVE-2016-9794, CVE-2016-9806, CVE-2016-9919, CVE-2017-0605, CVE-2017-0627, CVE-2017-0750, CVE-2017-0786, CVE-2017-0861, CVE-2017-1000, CVE-2017-1000111, CVE-2017-1000112, CVE-2017-1000251, CVE-2017-1000252, CVE-2017-1000253, CVE-2017-1000255, CVE-2017-1000363, CVE-2017-1000364, CVE-2017-1000365, CVE-2017-1000370, CVE-2017-1000371, CVE-2017-1000379, CVE-2017-1000380, CVE-2017-1000405, CVE-2017-1000407, CVE-2017-1000410, CVE-2017-10661, CVE-2017-10662, CVE-2017-10663, CVE-2017-10810, CVE-2017-10911, CVE-2017-11089, CVE-2017-11176, CVE-2017-11472, CVE-2017-11473, CVE-2017-11600, CVE-2017-12134, CVE-2017-12146, CVE-2017-12153, CVE-2017-12154, CVE-2017-12168, CVE-2017-12188, CVE-2017-12190, CVE-2017-12192, CVE-2017-12193, CVE-2017-12762, CVE-2017-13080, CVE-2017-13166, CVE-2017-13167, CVE-2017-13168, CVE-2017-13215, CVE-2017-13216, CVE-2017-13220, CVE-2017-13305, CVE-2017-13686, CVE-2017-13695, CVE-2017-13715, CVE-2017-14051, CVE-2017-14106, CVE-2017-14140, CVE-2017-14156, CVE-2017-14340, CVE-2017-14489, CVE-2017-14497, CVE-2017-14954, CVE-2017-14991, CVE-2017-15102, CVE-2017-15115, CVE-2017-15116, CVE-2017-15121, CVE-2017-15126, CVE-2017-15127, CVE-2017-15128, CVE-2017-15129, CVE-2017-15265, CVE-2017-15274, CVE-2017-15299, CVE-2017-15306, CVE-2017-15537, CVE-2017-15649, CVE-2017-15868, CVE-2017-15951, CVE-2017-16525, CVE-2017-16526, CVE-2017-16527, CVE-2017-16528, CVE-2017-16529, CVE-2017-16530, CVE-2017-16531, CVE-2017-16532, CVE-2017-16533, CVE-2017-16534, CVE-2017-16535, CVE-2017-16536, CVE-2017-16537, CVE-2017-16538, CVE-2017-16643, CVE-2017-16644, CVE-2017-16645, CVE-2017-16646, CVE-2017-16647, CVE-2017-16648, CVE-2017-16649, CVE-2017-16650, CVE-2017-16911, CVE-2017-16912, CVE-2017-16913, CVE-2017-16914, CVE-2017-16939, CVE-2017-16994, CVE-2017-16995, CVE-2017-16996, CVE-2017-17052, CVE-2017-17053, CVE-2017-17448, CVE-2017-17449, CVE-2017-17450, CVE-2017-17558, CVE-2017-17712, CVE-2017-17741, CVE-2017-17805, CVE-2017-17806, CVE-2017-17807, CVE-2017-17852, CVE-2017-17853, CVE-2017-17854, CVE-2017-17855, CVE-2017-17856, CVE-2017-17857, CVE-2017-17862, CVE-2017-17863, CVE-2017-17864, CVE-2017-17975, CVE-2017-18017, CVE-2017-18075, CVE-2017-18079, CVE-2017-18174, CVE-2017-18193, CVE-2017-18200, CVE-2017-18202, CVE-2017-18203, CVE-2017-18204, CVE-2017-18208, CVE-2017-18216, CVE-2017-18218, CVE-2017-18221, CVE-2017-18222, CVE-2017-18224, CVE-2017-18232, CVE-2017-18241, CVE-2017-18249, CVE-2017-18255, CVE-2017-18257, CVE-2017-18261, CVE-2017-18270, CVE-2017-18344, CVE-2017-18360, CVE-2017-18379, CVE-2017-18509, CVE-2017-18549, CVE-2017-18550, CVE-2017-18551, CVE-2017-18552, CVE-2017-18595, CVE-2017-2583, CVE-2017-2584, CVE-2017-2596, CVE-2017-2618, CVE-2017-2634, CVE-2017-2636, CVE-2017-2647, CVE-2017-2671, CVE-2017-5123, CVE-2017-5546, CVE-2017-5547, CVE-2017-5548, CVE-2017-5549, CVE-2017-5550, CVE-2017-5551, CVE-2017-5576, CVE-2017-5577, CVE-2017-5669, CVE-2017-5715, CVE-2017-5753, CVE-2017-5754, CVE-2017-5897, CVE-2017-5967, CVE-2017-5970, CVE-2017-5972, CVE-2017-5986, CVE-2017-6001, CVE-2017-6074, CVE-2017-6214, CVE-2017-6345, CVE-2017-6346, CVE-2017-6347, CVE-2017-6348, CVE-2017-6353, CVE-2017-6874, CVE-2017-6951, CVE-2017-7184, CVE-2017-7187, CVE-2017-7261, CVE-2017-7273, CVE-2017-7277, CVE-

2017-7294, CVE-2017-7308, CVE-2017-7346, CVE-2017-7374, CVE-2017-7472, CVE-2017-7477, CVE-2017-7482, CVE-2017-7487, CVE-2017-7495, CVE-2017-7518, CVE-2017-7533, CVE-2017-7541, CVE-2017-7542, CVE-2017-7558, CVE-2017-7616, CVE-2017-7618, CVE-2017-7645, CVE-2017-7889, CVE-2017-7895, CVE-2017-7979, CVE-2017-8061, CVE-2017-8062, CVE-2017-8063, CVE-2017-8064, CVE-2017-8065, CVE-2017-8066, CVE-2017-8067, CVE-2017-8068, CVE-2017-8069, CVE-2017-8070, CVE-2017-8071, CVE-2017-8072, CVE-2017-8106, CVE-2017-8240, CVE-2017-8797, CVE-2017-8824, CVE-2017-8831, CVE-2017-8890, CVE-2017-8924, CVE-2017-8925, CVE-2017-9059, CVE-2017-9074, CVE-2017-9075, CVE-2017-9076, CVE-2017-9077, CVE-2017-9150, CVE-2017-9211, CVE-2017-9242, CVE-2017-9605, CVE-2017-9725, CVE-2017-9984, CVE-2017-9985, CVE-2017-9986, CVE-2018-1000004, CVE-2018-1000026, CVE-2018-1000028, CVE-2018-1000199, CVE-2018-1000200, CVE-2018-1000204, CVE-2018-10021, CVE-2018-10074, CVE-2018-10087, CVE-2018-10124, CVE-2018-10322, CVE-2018-10323, CVE-2018-1065, CVE-2018-1066, CVE-2018-10675, CVE-2018-1068, CVE-2018-10840, CVE-2018-10853, CVE-2018-1087, CVE-2018-10876, CVE-2018-10877, CVE-2018-10878, CVE-2018-10879, CVE-2018-10880, CVE-2018-10881, CVE-2018-10882, CVE-2018-10883, CVE-2018-10901, CVE-2018-10902, CVE-2018-1091, CVE-2018-1092, CVE-2018-1093, CVE-2018-10938, CVE-2018-1094, CVE-2018-10940, CVE-2018-1095, CVE-2018-1108, CVE-2018-1118, CVE-2018-1120, CVE-2018-11232, CVE-2018-1128, CVE-2018-1129, CVE-2018-1130, CVE-2018-11412, CVE-2018-11506, CVE-2018-11508, CVE-2018-12126, CVE-2018-12127, CVE-2018-12130, CVE-2018-12207, CVE-2018-12232, CVE-2018-12233, CVE-2018-12633, CVE-2018-12714, CVE-2018-12896, CVE-2018-12904, CVE-2018-13053, CVE-2018-13093, CVE-2018-13094, CVE-2018-13095, CVE-2018-13096, CVE-2018-13097, CVE-2018-13098, CVE-2018-13099, CVE-2018-13100, CVE-2018-13405, CVE-2018-13406, CVE-2018-14609, CVE-2018-14610, CVE-2018-14611, CVE-2018-14612, CVE-2018-14613, CVE-2018-14614, CVE-2018-14615, CVE-2018-14616, CVE-2018-14617, CVE-2018-14619, CVE-2018-14625, CVE-2018-14633, CVE-2018-14634, CVE-2018-14641, CVE-2018-14646, CVE-2018-14656, CVE-2018-14678, CVE-2018-14734, CVE-2018-15471, CVE-2018-15572, CVE-2018-15594, CVE-2018-16276, CVE-2018-16597, CVE-2018-16658, CVE-2018-16862, CVE-2018-16871, CVE-2018-16880, CVE-2018-16882, CVE-2018-16884, CVE-2018-17182, CVE-2018-17972, CVE-2018-18021, CVE-2018-18281, CVE-2018-18386, CVE-2018-18397, CVE-2018-18445, CVE-2018-18559, CVE-2018-18690, CVE-2018-18710, CVE-2018-18955, CVE-2018-19406, CVE-2018-19407, CVE-2018-19824, CVE-2018-19854, CVE-2018-19985, CVE-2018-20169, CVE-2018-20449, CVE-2018-20509, CVE-2018-20510, CVE-2018-20511, CVE-2018-20669, CVE-2018-20784, CVE-2018-20836, CVE-2018-20854, CVE-2018-20855, CVE-2018-20856, CVE-2018-20961, CVE-2018-20976, CVE-2018-21008, CVE-2018-25015, CVE-2018-25020, CVE-2018-3620, CVE-2018-3639, CVE-2018-3646, CVE-2018-3665, CVE-2018-3693, CVE-2018-5332, CVE-2018-5333, CVE-2018-5344, CVE-2018-5390, CVE-2018-5391, CVE-2018-5703, CVE-2018-5750, CVE-2018-5803, CVE-2018-5814, CVE-2018-5848, CVE-2018-5873, CVE-2018-5953, CVE-2018-5995, CVE-2018-6412, CVE-2018-6554, CVE-2018-6555, CVE-2018-6927, CVE-2018-7191, CVE-2018-7273, CVE-2018-7480, CVE-2018-7492, CVE-2018-7566, CVE-2018-7740, CVE-2018-7754, CVE-2018-7755, CVE-2018-7757, CVE-2018-7995, CVE-2018-8043, CVE-2018-8087, CVE-2018-8781, CVE-2018-8822, CVE-2018-8897, CVE-2018-9363, CVE-2018-9385, CVE-2018-9415, CVE-2018-9422, CVE-2018-9465, CVE-2018-9516, CVE-2018-9517, CVE-2018-9518 and CVE-2018-9568

- **linux-yocto/6.1 (Continued):** Ignore CVE-2019-0136, CVE-2019-0145, CVE-2019-0146, CVE-2019-0147, CVE-2019-0148, CVE-2019-0149, CVE-2019-0154, CVE-2019-0155, CVE-2019-10124, CVE-2019-10125, CVE-2019-10126, CVE-2019-10142, CVE-2019-10207, CVE-2019-10220, CVE-2019-10638, CVE-2019-10639, CVE-2019-11085, CVE-2019-11091, CVE-2019-11135, CVE-2019-11190,



CVE-2019-11191, CVE-2019-1125, CVE-2019-11477, CVE-2019-11478, CVE-2019-11479, CVE-2019-11486, CVE-2019-11487, CVE-2019-11599, CVE-2019-11683, CVE-2019-11810, CVE-2019-11811, CVE-2019-11815, CVE-2019-11833, CVE-2019-11884, CVE-2019-12378, CVE-2019-12379, CVE-2019-12380, CVE-2019-12381, CVE-2019-12382, CVE-2019-12454, CVE-2019-12455, CVE-2019-12614, CVE-2019-12615, CVE-2019-12817, CVE-2019-12818, CVE-2019-12819, CVE-2019-12881, CVE-2019-12984, CVE-2019-13233, CVE-2019-13272, CVE-2019-13631, CVE-2019-13648, CVE-2019-14283, CVE-2019-14284, CVE-2019-14615, CVE-2019-14763, CVE-2019-14814, CVE-2019-14815, CVE-2019-14816, CVE-2019-14821, CVE-2019-14835, CVE-2019-14895, CVE-2019-14896, CVE-2019-14897, CVE-2019-14901, CVE-2019-15030, CVE-2019-15031, CVE-2019-15090, CVE-2019-15098, CVE-2019-15099, CVE-2019-15117, CVE-2019-15118, CVE-2019-15211, CVE-2019-15212, CVE-2019-15213, CVE-2019-15214, CVE-2019-15215, CVE-2019-15216, CVE-2019-15217, CVE-2019-15218, CVE-2019-15219, CVE-2019-15220, CVE-2019-15221, CVE-2019-15222, CVE-2019-15223, CVE-2019-15291, CVE-2019-15292, CVE-2019-15504, CVE-2019-15505, CVE-2019-15538, CVE-2019-15666, CVE-2019-15794, CVE-2019-15807, CVE-2019-15916, CVE-2019-15917, CVE-2019-15918, CVE-2019-15919, CVE-2019-15920, CVE-2019-15921, CVE-2019-15922, CVE-2019-15923, CVE-2019-15924, CVE-2019-15925, CVE-2019-15926, CVE-2019-15927, CVE-2019-16229, CVE-2019-16230, CVE-2019-16231, CVE-2019-16232, CVE-2019-16233, CVE-2019-16234, CVE-2019-16413, CVE-2019-16714, CVE-2019-16746, CVE-2019-16921, CVE-2019-16994, CVE-2019-16995, CVE-2019-17052, CVE-2019-17053, CVE-2019-17054, CVE-2019-17055, CVE-2019-17056, CVE-2019-17075, CVE-2019-17133, CVE-2019-17351, CVE-2019-17666, CVE-2019-18198, CVE-2019-18282, CVE-2019-18660, CVE-2019-18675, CVE-2019-18683, CVE-2019-18786, CVE-2019-18805, CVE-2019-18806, CVE-2019-18807, CVE-2019-18808, CVE-2019-18809, CVE-2019-18810, CVE-2019-18811, CVE-2019-18812, CVE-2019-18813, CVE-2019-18814, CVE-2019-18885, CVE-2019-19036, CVE-2019-19037, CVE-2019-19039, CVE-2019-19043, CVE-2019-19044, CVE-2019-19045, CVE-2019-19046, CVE-2019-19047, CVE-2019-19048, CVE-2019-19049, CVE-2019-19050, CVE-2019-19051, CVE-2019-19052, CVE-2019-19053, CVE-2019-19054, CVE-2019-19055, CVE-2019-19056, CVE-2019-19057, CVE-2019-19058, CVE-2019-19059, CVE-2019-19060, CVE-2019-19061, CVE-2019-19062, CVE-2019-19063, CVE-2019-19064, CVE-2019-19065, CVE-2019-19066, CVE-2019-19067, CVE-2019-19068, CVE-2019-19069, CVE-2019-19070, CVE-2019-19071, CVE-2019-19072, CVE-2019-19073, CVE-2019-19074, CVE-2019-19075, CVE-2019-19076, CVE-2019-19077, CVE-2019-19078, CVE-2019-19079, CVE-2019-19080, CVE-2019-19081, CVE-2019-19082, CVE-2019-19083, CVE-2019-19227, CVE-2019-19241, CVE-2019-19252, CVE-2019-19318, CVE-2019-19319, CVE-2019-19332, CVE-2019-19338, CVE-2019-19377, CVE-2019-19447, CVE-2019-19448, CVE-2019-19449, CVE-2019-19462, CVE-2019-19523, CVE-2019-19524, CVE-2019-19525, CVE-2019-19526, CVE-2019-19527, CVE-2019-19528, CVE-2019-19529, CVE-2019-19530, CVE-2019-19531, CVE-2019-19532, CVE-2019-19533, CVE-2019-19534, CVE-2019-19535, CVE-2019-19536, CVE-2019-19537, CVE-2019-19543, CVE-2019-19602, CVE-2019-19767, CVE-2019-19768, CVE-2019-19769, CVE-2019-19770, CVE-2019-19807, CVE-2019-19813, CVE-2019-19815, CVE-2019-19816, CVE-2019-19922, CVE-2019-19927, CVE-2019-19947, CVE-2019-19965, CVE-2019-19966, CVE-2019-1999, CVE-2019-20054, CVE-2019-20095, CVE-2019-20096, CVE-2019-2024, CVE-2019-2025, CVE-2019-20422, CVE-2019-2054, CVE-2019-20636, CVE-2019-20806, CVE-2019-20810, CVE-2019-20811, CVE-2019-20812, CVE-2019-20908, CVE-2019-20934, CVE-2019-2101, CVE-2019-2181, CVE-2019-2182, CVE-2019-2213, CVE-2019-2214, CVE-2019-2215, CVE-2019-25044, CVE-2019-25045, CVE-2019-3016, CVE-2019-3459, CVE-2019-3460, CVE-2019-3701, CVE-2019-3819, CVE-2019-3837, CVE-2019-3846, CVE-2019-3874, CVE-2019-3882, CVE-2019-3887, CVE-2019-3892, CVE-2019-3896, CVE-2019-3900, CVE-2019-3901, CVE-2019-5108, CVE-2019-6133, CVE-2019-6974, CVE-

2019-7221, CVE-2019-7222, CVE-2019-7308, CVE-2019-8912, CVE-2019-8956, CVE-2019-8980, CVE-2019-9003, CVE-2019-9162, CVE-2019-9213, CVE-2019-9245, CVE-2019-9444, CVE-2019-9445, CVE-2019-9453, CVE-2019-9454, CVE-2019-9455, CVE-2019-9456, CVE-2019-9457, CVE-2019-9458, CVE-2019-9466, CVE-2019-9500, CVE-2019-9503, CVE-2019-9506, CVE-2019-9857, CVE-2020-0009, CVE-2020-0030, CVE-2020-0041, CVE-2020-0066, CVE-2020-0067, CVE-2020-0110, CVE-2020-0255, CVE-2020-0305, CVE-2020-0404, CVE-2020-0423, CVE-2020-0427, CVE-2020-0429, CVE-2020-0430, CVE-2020-0431, CVE-2020-0432, CVE-2020-0433, CVE-2020-0435, CVE-2020-0444, CVE-2020-0465, CVE-2020-0466, CVE-2020-0543, CVE-2020-10135, CVE-2020-10690, CVE-2020-10711, CVE-2020-10720, CVE-2020-10732, CVE-2020-10742, CVE-2020-10751, CVE-2020-10757, CVE-2020-10766, CVE-2020-10767, CVE-2020-10768, CVE-2020-10769, CVE-2020-10773, CVE-2020-10781, CVE-2020-10942, CVE-2020-11494, CVE-2020-11565, CVE-2020-11608, CVE-2020-11609, CVE-2020-11668, CVE-2020-11669, CVE-2020-11884, CVE-2020-12114, CVE-2020-12351, CVE-2020-12352, CVE-2020-12362, CVE-2020-12363, CVE-2020-12364, CVE-2020-12464, CVE-2020-12465, CVE-2020-12652, CVE-2020-12653, CVE-2020-12654, CVE-2020-12655, CVE-2020-12656, CVE-2020-12657, CVE-2020-12659, CVE-2020-12768, CVE-2020-12769, CVE-2020-12770, CVE-2020-12771, CVE-2020-12826, CVE-2020-12888, CVE-2020-12912, CVE-2020-13143, CVE-2020-13974, CVE-2020-14305, CVE-2020-14314, CVE-2020-14331, CVE-2020-14351, CVE-2020-14353, CVE-2020-14356, CVE-2020-14381, CVE-2020-14385, CVE-2020-14386, CVE-2020-14390, CVE-2020-14416, CVE-2020-15393, CVE-2020-15436, CVE-2020-15437, CVE-2020-15780, CVE-2020-15852, CVE-2020-16119, CVE-2020-16120, CVE-2020-16166, CVE-2020-1749, CVE-2020-24394, CVE-2020-24490, CVE-2020-24504, CVE-2020-24586, CVE-2020-24587, CVE-2020-24588, CVE-2020-25211, CVE-2020-25212, CVE-2020-25221, CVE-2020-25284, CVE-2020-25285, CVE-2020-25639, CVE-2020-25641, CVE-2020-25643, CVE-2020-25645, CVE-2020-25656, CVE-2020-25668, CVE-2020-25669, CVE-2020-25670, CVE-2020-25671, CVE-2020-25672, CVE-2020-25673, CVE-2020-25704, CVE-2020-25705, CVE-2020-26088, CVE-2020-26139, CVE-2020-26141, CVE-2020-26145, CVE-2020-26147, CVE-2020-26541, CVE-2020-26555, CVE-2020-26558, CVE-2020-27066, CVE-2020-27067, CVE-2020-27068, CVE-2020-27152, CVE-2020-27170, CVE-2020-27171, CVE-2020-27194, CVE-2020-2732, CVE-2020-27673, CVE-2020-27675, CVE-2020-27777, CVE-2020-27784, CVE-2020-27786, CVE-2020-27815, CVE-2020-27820, CVE-2020-27825, CVE-2020-27830, CVE-2020-27835, CVE-2020-28097, CVE-2020-28374, CVE-2020-28588, CVE-2020-28915, CVE-2020-28941, CVE-2020-28974, CVE-2020-29368, CVE-2020-29369, CVE-2020-29370, CVE-2020-29371, CVE-2020-29372, CVE-2020-29373, CVE-2020-29374, CVE-2020-29534, CVE-2020-29568, CVE-2020-29569, CVE-2020-29660, CVE-2020-29661, CVE-2020-35499, CVE-2020-35508, CVE-2020-35513, CVE-2020-35519, CVE-2020-36158, CVE-2020-36310, CVE-2020-36311, CVE-2020-36312, CVE-2020-36313, CVE-2020-36322, CVE-2020-36385, CVE-2020-36386, CVE-2020-36387, CVE-2020-36516, CVE-2020-36557, CVE-2020-36558, CVE-2020-36691, CVE-2020-36694, CVE-2020-36766, CVE-2020-3702, CVE-2020-4788, CVE-2020-7053, CVE-2020-8428, CVE-2020-8647, CVE-2020-8648, CVE-2020-8649, CVE-2020-8694, CVE-2020-8834, CVE-2020-8835, CVE-2020-8992, CVE-2020-9383, CVE-2020-9391, CVE-2021-0129, CVE-2021-0342, CVE-2021-0447, CVE-2021-0448, CVE-2021-0512, CVE-2021-0605, CVE-2021-0707, CVE-2021-0920, CVE-2021-0929, CVE-2021-0935, CVE-2021-0937, CVE-2021-0938, CVE-2021-0941, CVE-2021-1048, CVE-2021-20177, CVE-2021-20194, CVE-2021-20226, CVE-2021-20239, CVE-2021-20261, CVE-2021-20265, CVE-2021-20268, CVE-2021-20292, CVE-2021-20317, CVE-2021-20320, CVE-2021-20321, CVE-2021-20322, CVE-2021-21781, CVE-2021-22543, CVE-2021-22555, CVE-2021-22600, CVE-2021-23133, CVE-2021-23134, CVE-2021-26401, CVE-2021-26708, CVE-2021-26930, CVE-2021-26931, CVE-2021-26932, CVE-2021-27363, CVE-2021-27364, CVE-2021-27365, CVE-2021-28038, CVE-2021-28039, CVE-2021-28375, CVE-2021-

28660, CVE-2021-28688, CVE-2021-28691, CVE-2021-28711, CVE-2021-28712, CVE-2021-28713, CVE-2021-28714, CVE-2021-28715, CVE-2021-28950, CVE-2021-28951, CVE-2021-28952, CVE-2021-28964, CVE-2021-28971, CVE-2021-28972, CVE-2021-29154, CVE-2021-29155, CVE-2021-29264, CVE-2021-29265, CVE-2021-29266, CVE-2021-29646, CVE-2021-29647, CVE-2021-29648, CVE-2021-29649, CVE-2021-29650, CVE-2021-29657, CVE-2021-30002, CVE-2021-30178, CVE-2021-31440, CVE-2021-3178, CVE-2021-31829, CVE-2021-31916, CVE-2021-32078, CVE-2021-32399, CVE-2021-32606, CVE-2021-33033, CVE-2021-33034, CVE-2021-33061, CVE-2021-33098, CVE-2021-33135, CVE-2021-33200, CVE-2021-3347, CVE-2021-3348, CVE-2021-33624, CVE-2021-33655, CVE-2021-33656, CVE-2021-33909, CVE-2021-3411, CVE-2021-3428, CVE-2021-3444, CVE-2021-34556, CVE-2021-34693, CVE-2021-3483, CVE-2021-34866, CVE-2021-3489, CVE-2021-3490, CVE-2021-3491, CVE-2021-3493, CVE-2021-34981, CVE-2021-3501, CVE-2021-35039, CVE-2021-3506, CVE-2021-3543, CVE-2021-35477, CVE-2021-3564, CVE-2021-3573, CVE-2021-3587, CVE-2021-3600, CVE-2021-3609, CVE-2021-3612, CVE-2021-3635, CVE-2021-3640, CVE-2021-3653, CVE-2021-3655, CVE-2021-3656, CVE-2021-3659, CVE-2021-3669, CVE-2021-3679, CVE-2021-3715, CVE-2021-37159, CVE-2021-3732, CVE-2021-3736, CVE-2021-3739, CVE-2021-3743, CVE-2021-3744, CVE-2021-3752, CVE-2021-3753, CVE-2021-37576, CVE-2021-3759, CVE-2021-3760, CVE-2021-3764, CVE-2021-3772, CVE-2021-38160, CVE-2021-38166, CVE-2021-38198, CVE-2021-38199, CVE-2021-38200, CVE-2021-38201, CVE-2021-38202, CVE-2021-38203, CVE-2021-38204, CVE-2021-38205, CVE-2021-38206, CVE-2021-38207, CVE-2021-38208, CVE-2021-38209, CVE-2021-38300, CVE-2021-3894, CVE-2021-3896, CVE-2021-3923, CVE-2021-39633, CVE-2021-39634, CVE-2021-39636, CVE-2021-39648, CVE-2021-39656, CVE-2021-39657, CVE-2021-39685, CVE-2021-39686, CVE-2021-39698, CVE-2021-39711, CVE-2021-39713, CVE-2021-39714, CVE-2021-4001, CVE-2021-4002, CVE-2021-4023, CVE-2021-4028, CVE-2021-4032, CVE-2021-4037, CVE-2021-40490, CVE-2021-4083, CVE-2021-4090, CVE-2021-4093, CVE-2021-4095, CVE-2021-41073, CVE-2021-4135, CVE-2021-4148, CVE-2021-4149, CVE-2021-4150, CVE-2021-4154, CVE-2021-4155, CVE-2021-4157, CVE-2021-4159, CVE-2021-41864, CVE-2021-4197, CVE-2021-42008, CVE-2021-4202, CVE-2021-4203, CVE-2021-4204, CVE-2021-4218, CVE-2021-42252, CVE-2021-42327, CVE-2021-42739, CVE-2021-43056, CVE-2021-43057, CVE-2021-43267, CVE-2021-43389, CVE-2021-43975, CVE-2021-43976, CVE-2021-44733, CVE-2021-44879, CVE-2021-45095, CVE-2021-45100, CVE-2021-45402, CVE-2021-45469, CVE-2021-45480, CVE-2021-45485, CVE-2021-45486, CVE-2021-45868, CVE-2021-46283, CVE-2022-0001, CVE-2022-0002, CVE-2022-0168, CVE-2022-0171, CVE-2022-0185, CVE-2022-0264, CVE-2022-0286, CVE-2022-0322, CVE-2022-0330, CVE-2022-0382, CVE-2022-0433, CVE-2022-0435, CVE-2022-0480, CVE-2022-0487, CVE-2022-0492, CVE-2022-0494, CVE-2022-0500, CVE-2022-0516, CVE-2022-0617, CVE-2022-0644, CVE-2022-0646, CVE-2022-0742, CVE-2022-0812, CVE-2022-0847, CVE-2022-0850, CVE-2022-0854, CVE-2022-0995, CVE-2022-0998, CVE-2022-1011, CVE-2022-1012, CVE-2022-1015, CVE-2022-1016, CVE-2022-1043, CVE-2022-1048, CVE-2022-1055, CVE-2022-1158, CVE-2022-1184, CVE-2022-1195, CVE-2022-1198, CVE-2022-1199, CVE-2022-1204, CVE-2022-1205, CVE-2022-1263, CVE-2022-1280, CVE-2022-1353, CVE-2022-1419, CVE-2022-1462, CVE-2022-1508, CVE-2022-1516, CVE-2022-1651, CVE-2022-1652, CVE-2022-1671, CVE-2022-1678, CVE-2022-1679, CVE-2022-1729, CVE-2022-1734, CVE-2022-1786, CVE-2022-1789, CVE-2022-1836, CVE-2022-1852, CVE-2022-1882, CVE-2022-1943, CVE-2022-1966, CVE-2022-1972, CVE-2022-1973, CVE-2022-1974, CVE-2022-1975, CVE-2022-1976, CVE-2022-1998, CVE-2022-20008, CVE-2022-20132, CVE-2022-20141, CVE-2022-20148, CVE-2022-20153, CVE-2022-20154, CVE-2022-20158, CVE-2022-20166, CVE-2022-20368, CVE-2022-20369, CVE-2022-20409, CVE-2022-20421, CVE-2022-20422, CVE-2022-20423, CVE-2022-20424, CVE-2022-20565, CVE-2022-20566, CVE-2022-20567, CVE-2022-20568, CVE-2022-20572, CVE-2022-

2078, CVE-2022-21123, CVE-2022-21125, CVE-2022-21166, CVE-2022-21385, CVE-2022-21499, CVE-2022-21505, CVE-2022-2153, CVE-2022-2196, CVE-2022-22942, CVE-2022-23036, CVE-2022-23037, CVE-2022-23038, CVE-2022-23039, CVE-2022-23040, CVE-2022-23041, CVE-2022-23042, CVE-2022-2308, CVE-2022-2318, CVE-2022-23222, CVE-2022-2327, CVE-2022-2380, CVE-2022-23816, CVE-2022-23960, CVE-2022-24122, CVE-2022-24448, CVE-2022-24958, CVE-2022-24959, CVE-2022-2503, CVE-2022-25258, CVE-2022-25375, CVE-2022-25636, CVE-2022-2585, CVE-2022-2586, CVE-2022-2588, CVE-2022-2590, CVE-2022-2602, CVE-2022-26365, CVE-2022-26373, CVE-2022-2639, CVE-2022-26490, CVE-2022-2663, CVE-2022-26966, CVE-2022-27223, CVE-2022-27666, CVE-2022-27672, CVE-2022-2785, CVE-2022-27950, CVE-2022-28356, CVE-2022-28388, CVE-2022-28389, CVE-2022-28390, CVE-2022-2873, CVE-2022-28796, CVE-2022-28893, CVE-2022-2905, CVE-2022-29156, CVE-2022-2938, CVE-2022-29581, CVE-2022-29582, CVE-2022-2959, CVE-2022-2964, CVE-2022-2977, CVE-2022-2978, CVE-2022-29900, CVE-2022-29901, CVE-2022-2991, CVE-2022-29968, CVE-2022-3028, CVE-2022-30594, CVE-2022-3061, CVE-2022-3077, CVE-2022-3078, CVE-2022-3103, CVE-2022-3104, CVE-2022-3105, CVE-2022-3106, CVE-2022-3107, CVE-2022-3108, CVE-2022-3110, CVE-2022-3111, CVE-2022-3112, CVE-2022-3113, CVE-2022-3114, CVE-2022-3115, CVE-2022-3169, CVE-2022-3170, CVE-2022-3176, CVE-2022-3202, CVE-2022-32250, CVE-2022-32296, CVE-2022-3239, CVE-2022-32981, CVE-2022-3303, CVE-2022-3344, CVE-2022-33740, CVE-2022-33741, CVE-2022-33742, CVE-2022-33743, CVE-2022-33744, CVE-2022-33981, CVE-2022-3424, CVE-2022-3435, CVE-2022-34494, CVE-2022-34495, CVE-2022-34918, CVE-2022-3521, CVE-2022-3522, CVE-2022-3524, CVE-2022-3526, CVE-2022-3531, CVE-2022-3532, CVE-2022-3534, CVE-2022-3535, CVE-2022-3541, CVE-2022-3542, CVE-2022-3543, CVE-2022-3545, CVE-2022-3564, CVE-2022-3565, CVE-2022-3577, CVE-2022-3586, CVE-2022-3594, CVE-2022-3595, CVE-2022-36123, CVE-2022-3619, CVE-2022-3621, CVE-2022-3623, CVE-2022-3624, CVE-2022-3625, CVE-2022-3628, CVE-2022-36280, CVE-2022-3629, CVE-2022-3630, CVE-2022-3633, CVE-2022-3635, CVE-2022-3636, CVE-2022-3640, CVE-2022-3643, CVE-2022-3646, CVE-2022-3649, CVE-2022-36879, CVE-2022-36946, CVE-2022-3707, CVE-2022-38457, CVE-2022-3903, CVE-2022-3910, CVE-2022-39188, CVE-2022-39189, CVE-2022-39190, CVE-2022-3977, CVE-2022-39842, CVE-2022-40133, CVE-2022-40307, CVE-2022-40476, CVE-2022-40768, CVE-2022-4095, CVE-2022-40982, CVE-2022-41218, CVE-2022-41222, CVE-2022-4127, CVE-2022-4128, CVE-2022-4129, CVE-2022-4139, CVE-2022-41674, CVE-2022-41849, CVE-2022-41850, CVE-2022-41858, CVE-2022-42328, CVE-2022-42329, CVE-2022-42432, CVE-2022-4269, CVE-2022-42703, CVE-2022-42719, CVE-2022-42720, CVE-2022-42721, CVE-2022-42722, CVE-2022-42895, CVE-2022-42896, CVE-2022-43750, CVE-2022-4378, CVE-2022-4379, CVE-2022-4382, CVE-2022-43945, CVE-2022-45869, CVE-2022-45886, CVE-2022-45887, CVE-2022-45919, CVE-2022-45934, CVE-2022-4662, CVE-2022-4696, CVE-2022-4744, CVE-2022-47518, CVE-2022-47519, CVE-2022-47520, CVE-2022-47521, CVE-2022-47929, CVE-2022-47938, CVE-2022-47939, CVE-2022-47940, CVE-2022-47941, CVE-2022-47942, CVE-2022-47943, CVE-2022-47946, CVE-2022-4842, CVE-2022-48423, CVE-2022-48424, CVE-2022-48425, CVE-2022-48502, CVE-2023-0030, CVE-2023-0045, CVE-2023-0047, CVE-2023-0122, CVE-2023-0160, CVE-2023-0179, CVE-2023-0210, CVE-2023-0240, CVE-2023-0266, CVE-2023-0386, CVE-2023-0394, CVE-2023-0458, CVE-2023-0459, CVE-2023-0461, CVE-2023-0468, CVE-2023-0469, CVE-2023-0590, CVE-2023-0615, CVE-2023-1032, CVE-2023-1073, CVE-2023-1074, CVE-2023-1076, CVE-2023-1077, CVE-2023-1078, CVE-2023-1079, CVE-2023-1095, CVE-2023-1118, CVE-2023-1192, CVE-2023-1194, CVE-2023-1195, CVE-2023-1206, CVE-2023-1249, CVE-2023-1252, CVE-2023-1281, CVE-2023-1295, CVE-2023-1380, CVE-2023-1382, CVE-2023-1390, CVE-2023-1513, CVE-2023-1582, CVE-2023-1583, CVE-2023-1611, CVE-2023-1637, CVE-2023-1652, CVE-2023-1670, CVE-2023-1829, CVE-2023-1838, CVE-2023-1855, CVE-2023-1859, CVE-2023-1872, CVE-2023-1989, CVE-

CVE-2023-1990, CVE-2023-1998, CVE-2023-2002, CVE-2023-2006, CVE-2023-2007, CVE-2023-2008, CVE-2023-2019, CVE-2023-20569, CVE-2023-20588, CVE-2023-20593, CVE-2023-20928, CVE-2023-20938, CVE-2023-21102, CVE-2023-21106, CVE-2023-2124, CVE-2023-21255, CVE-2023-2156, CVE-2023-2162, CVE-2023-2163, CVE-2023-2166, CVE-2023-2177, CVE-2023-2194, CVE-2023-2235, CVE-2023-2236, CVE-2023-2248, CVE-2023-2269, CVE-2023-22995, CVE-2023-22996, CVE-2023-22997, CVE-2023-22998, CVE-2023-22999, CVE-2023-23000, CVE-2023-23001, CVE-2023-23002, CVE-2023-23003, CVE-2023-23004, CVE-2023-23006, CVE-2023-23454, CVE-2023-23455, CVE-2023-23559, CVE-2023-23586, CVE-2023-2430, CVE-2023-2483, CVE-2023-25012, CVE-2023-2513, CVE-2023-25775, CVE-2023-2598, CVE-2023-26544, CVE-2023-26545, CVE-2023-26605, CVE-2023-26606, CVE-2023-26607, CVE-2023-28327, CVE-2023-28328, CVE-2023-28410, CVE-2023-28464, CVE-2023-28466, CVE-2023-2860, CVE-2023-28772, CVE-2023-28866, CVE-2023-2898, CVE-2023-2985, CVE-2023-3006, CVE-2023-30456, CVE-2023-30772, CVE-2023-3090, CVE-2023-3106, CVE-2023-3111, CVE-2023-3117, CVE-2023-31248, CVE-2023-3141, CVE-2023-31436, CVE-2023-3159, CVE-2023-3161, CVE-2023-3212, CVE-2023-3220, CVE-2023-32233, CVE-2023-32247, CVE-2023-32248, CVE-2023-32250, CVE-2023-32252, CVE-2023-32254, CVE-2023-32257, CVE-2023-32258, CVE-2023-32269, CVE-2023-3268, CVE-2023-3269, CVE-2023-3312, CVE-2023-3317, CVE-2023-33203, CVE-2023-33250, CVE-2023-33288, CVE-2023-3338, CVE-2023-3355, CVE-2023-3357, CVE-2023-3358, CVE-2023-3359, CVE-2023-3389, CVE-2023-3390, CVE-2023-33951, CVE-2023-33952, CVE-2023-34255, CVE-2023-34256, CVE-2023-34319, CVE-2023-3439, CVE-2023-35001, CVE-2023-3567, CVE-2023-35788, CVE-2023-35823, CVE-2023-35824, CVE-2023-35826, CVE-2023-35828, CVE-2023-35829, CVE-2023-3609, CVE-2023-3610, CVE-2023-3611, CVE-2023-37453, CVE-2023-3772, CVE-2023-3773, CVE-2023-3776, CVE-2023-3777, CVE-2023-3812, CVE-2023-38409, CVE-2023-38426, CVE-2023-38427, CVE-2023-38428, CVE-2023-38429, CVE-2023-38430, CVE-2023-38431, CVE-2023-38432, CVE-2023-3863, CVE-2023-3865, CVE-2023-3866, CVE-2023-3867, CVE-2023-4004, CVE-2023-4015, CVE-2023-40283, CVE-2023-4128, CVE-2023-4132, CVE-2023-4147, CVE-2023-4155, CVE-2023-4194, CVE-2023-4206, CVE-2023-4207, CVE-2023-4208, CVE-2023-4273, CVE-2023-42752, CVE-2023-42753, CVE-2023-4385, CVE-2023-4387, CVE-2023-4389, CVE-2023-4394, CVE-2023-4459, CVE-2023-4569, CVE-2023-4611 and CVE-2023-4623

- `nghttp2`: Fix CVE-2023-35945
- `openssl`: Fix CVE-2023-2975, CVE-2023-3446, CVE-2023-3817, CVE-2023-4807 and CVE-2023-5363
- `pixman`: Ignore CVE-2023-37769
- `procps`: Fix CVE-2023-4016
- `python3-git`: Fix CVE-2023-40267, CVE-2023-40590 and CVE-2023-41040
- `python3-pygments`: Fix CVE-2022-40896
- `python3-urllib3`: Fix CVE-2023-43804 and CVE-2023-45803
- `python3`: Fix CVE-2023-24329 and CVE-2023-40217
- `qemu`: Fix CVE-2023-3180, CVE-2023-3354 and CVE-2023-42467
- `qemu`: Ignore CVE-2023-2680
- `screen`: Fix CVE-2023-24626
- `shadow`: Fix CVE-2023-4641

- tiff: Fix CVE-2023-40745 and CVE-2023-41175
- vim: Fix CVE-2023-3896, CVE-2023-4733, CVE-2023-4734, CVE-2023-4735, CVE-2023-4736, CVE-2023-4738, CVE-2023-4750, CVE-2023-4752, CVE-2023-4781, CVE-2023-5441 and CVE-2023-5535
- webkitgtk: Fix CVE-2023-32435 and CVE-2023-32439
- xserver-xorg: Fix CVE-2023-5367 and CVE-2023-5380

#### Fixes in Yocto-4.2.4

- README: Update to point to new contributor guide
- README: fix mail address in git example command
- SECURITY.md: Add file
- avahi: handle invalid service types gracefully
- bind: upgrade to 9.18.19
- bitbake.conf: add bunzip2 in *HOSTTOOLS*
- bitbake: Fix disk space monitoring on cephfs
- bitbake: SECURITY.md: add file
- brief-yoctoprojectqs: use new CDN mirror for sstate
- bsp-guide: bsp.rst: replace reference to wiki
- bsp-guide: bsp: skip Intel machines no longer supported in Poky
- build-appliance-image: Update to mickledore head revision
- build-sysroots: Add *SUMMARY* field
- build-sysroots: Ensure dependency chains are minimal
- build-sysroots: target or native sysroot population need to be selected explicitly
- buildtools-tarball: Add libacl
- busybox: Set PATH in syslog initscript
- busybox: remove coreutils dependency in busybox-ptest
- cmake.bbclass: fix allarch override syntax
- cml1: Fix KCONFIG\_CONFIG\_COMMAND not conveyed fully in do\_menuconfig
- contributor-guide/style-guide: Add a note about task idempotence
- contributor-guide/style-guide: Refer to recipes, not packages
- contributor-guide: deprecate "Accepted" patch status
- contributor-guide: discourage marking patches as Inappropriate
- contributor-guide: recipe-style-guide: add Upstream-Status
- contributor-guide: recipe-style-guide: add more patch tagging examples

- contributor-guide: recipe-style-guide: add section about CVE patches
- contributor-guide: style-guide: discourage using Pending patch status
- core-image-ptest: Define a fallback for *SUMMARY* field
- cve-check: add CVSS vector string to CVE database and reports
- cve-check: don't warn if a patch is remote
- cve-check: slightly more verbose warning when adding the same package twice
- cve-check: sort the package list in the JSON report
- cve-exclusion\_6.1.inc: update for 6.1.57
- dbus: add additional entries to *CVE\_PRODUCT*
- dbus: upgrade to 1.14.10
- dev-manual: add security team processes
- dev-manual: disk-space: improve wording for obsolete sstate cache files
- dev-manual: disk-space: mention faster "find" command to trim sstate cache
- dev-manual: fix testimage usage instructions
- dev-manual: layers: Add notes about layer.conf
- dev-manual: licenses: mention *SPDX* for license compliance
- dev-manual: new-recipe.rst fix inconsistency with contributor guide
- dev-manual: new-recipe.rst: add missing parenthesis to "Patching Code" section
- dev-manual: new-recipe.rst: replace reference to wiki
- dev-manual: remove unsupported :term: markup inside markup
- dev-manual: start.rst: remove obsolete reference
- ell: upgrade to 0.58
- externalsrc: fix dependency chain issues
- ffmpeg: upgrade to 5.1.3
- ffmpeg: avoid neon on unsupported machines
- file: fix call to localtime\_r()
- file: upgrade to 5.45
- fontcache.bbclass: avoid native recipes depending on target fontconfig
- gcc-crosssdk: ignore MULTILIB\_VARIANTS in signature computation
- gcc-runtime: remove bashism
- gcc: backport a fix for ICE caused by CVE-2023-4039.patch
- gcc: depend on zstd



- gdb: fix *RDEPENDS* for PACKAGECONFIG[tui]
- glib-2.0: libelf has a configure option now, specify it
- glibc: stable 2.37 branch updates
- gnupg: Fix reproducibility failure
- gnupg: upgrade to 2.4.3
- go: upgrade to 1.20.7
- graphene: fix runtime detection of IEEE754 behaviour
- gstreamer: upgrade to 1.22.6
- gtk4: upgrade to 4.10.5
- gzip: upgrade to 1.13
- igt-gpu-tools: do not write shortened git commit hash into binaries
- inetutils: don't guess target paths
- inetutils: remove obsolete cruft from do\_configure
- insane.bbclass: Count raw bytes in shebang-size
- kernel.bbclass: Add force flag to rm calls
- lib/package\_manager: Improve repo artefact filtering
- libc-test: Run as non-root user
- libconvert-asn1-perl: upgrade to 0.34
- libevent: fix patch Upstream-Status
- libgudev: explicitly disable tests and vapi
- librepo: upgrade to 1.15.2
- librsvg: upgrade to 2.54.6
- libsndfile1: upgrade to 1.2.2
- libsoup-2.4: Only specify --cross-file when building for target
- libsoup-2.4: update *PACKAGECONFIG*
- libx11: upgrade to 1.8.7
- libxkbcommon: add *CVE\_PRODUCT*
- libxpm: upgrade to 3.5.17
- linux-firmware: add firmware files for NXP BT chipsets
- linux-firmware: package Dragonboard 845c sensors DSP firmware
- linux-firmware: package audio topology for Lenovo X13s
- linux-firmware: upgrade to 20230804



- linux-yocto/5.15: update to v5.15.133
- linux-yocto/6.1: fix CONFIG\_F2FS\_IO\_TRACE configuration warning
- linux-yocto/6.1: fix IRQ-80 warnings
- linux-yocto/6.1: fix uninitialized read in nohz\_full/isolcpus setup
- linux-yocto/6.1: tiny: fix arm 32 boot
- linux-yocto/6.1: update to v6.1.57
- linux-yocto: add script to generate kernel *CVE\_CHECK\_IGNORE* entries
- linux-yocto: make sure the pahole-native available before do\_kernel\_configme
- linux/cve-exclusion: add generated CVE\_CHECK\_IGNOREs
- linux/generate-cve-exclusions: fix mishandling of boundary values
- linux/generate-cve-exclusions: print the generated time in UTC
- manuals: add new contributor guide
- manuals: correct "yocto-linux" by "linux-yocto"
- mdadm: Disable further tests due to intermittent failures
- mdadm: skip running 04update-uuid and 07revert-inplace testcases
- migration-guides: add release notes for 4.0.12
- migration-guides: add release notes for 4.0.13
- migration-guides: add release notes for 4.2.3
- mpfr: upgrade to 4.2.1
- multilib.conf: explicitly make MULTILIB\_VARIANTS vardeps on MULTILIBS
- nativesdk-intercept: Fix bad intercept chgrp/chown logic
- nettle: avoid neon on unsupported machines
- oe-depends-dot: improve '-w' behavior
- oeqa dnf\_runtime.py: fix HTTP server IP address and port
- oeqa selftest context.py: remove warning from missing meta-selftest
- oeqa selftest context.py: whitespace fix
- oeqa/concurrencytest: Remove invalid buffering option
- oeqa/selftest/context.py: check git command return values
- oeqa/selftest/wic: Improve assertTrue calls
- oeqa/selftest: Fix broken symlink removal handling
- oeqa/utlils/gitarchive: Handle broken commit counts in results repo
- openssl: upgrade to 3.1.4

- openssl: build and install manpages only if they are enabled
- openssl: ensure all ptest fails are caught
- openssl: parallelize tests
- overview: Add note about non-reproducibility side effects
- packages.bbclass: Correct the check for conflicts with renamed packages
- pango: explicitly enable/disable libthai
- patch.py: use --absolute-git-dir instead of --show-toplevel to retrieve gitdir
- pixman: Remove duplication of license MIT
- pixman: avoid neon on unsupported machines
- poky.conf: bump version for 4.2.4 release
- profile-manual: aesthetic cleanups
- pseudo: Fix to work with glibc 2.38
- ptest: report tests that were killed on timeout
- python3-git: upgrade to 3.1.37
- python3-urllib3: update to v1.26.18
- python3: upgrade to 3.11.5
- qemu: fix "Bad FPU state detected" fault on qemu-system-i386
- ref-manual: Fix *PACKAGECONFIG* term and add an example
- ref-manual: Warn about *COMPATIBLE\_MACHINE* skipping native recipes
- ref-manual: point outdated link to the new location
- ref-manual: releases.svg: Scarthgap is now version 5.0
- ref-manual: system-requirements: update supported distros
- ref-manual: variables: add *RECIPE\_SYSROOT* and *RECIPE\_SYSROOT\_NATIVE*
- ref-manual: variables: add *TOOLCHAIN\_OPTIONS* variable
- ref-manual: variables: add example for *SYSROOT\_DIRS* variable
- ref-manual: variables: provide no-match example for *COMPATIBLE\_MACHINE*
- resulttool/report: Avoid divide by zero
- runqemu: check permissions of available render nodes as well as their presence
- screen: upgrade to 4.9.1
- scripts/create-pull-request: update URLs to git repositories
- sdk-manual: appendix-obtain: improve and update descriptions
- sdk-manual: extensible.rst: fix multiple formatting issues

- shadow: fix patch Upstream-Status
- strace: parallelize ptest
- sudo: upgrade to 1.9.15p2
- systemd-bootchart: musl fixes have been rejected upstream
- systemd: backport patch to fix warning in systemd-vconsole-setup
- tar: upgrade to 1.35
- tcl: Add a way to skip ptests
- tcl: prevent installing another copy of tzdata
- template: fix typo in section header
- test-manual: reproducible-builds: stop mentioning LTO bug
- uboot-extlinux-config.bbclass: fix missed override syntax migration
- vim: upgrade to 9.0.2048
- vim: update obsolete comment
- wayland-utils: add libdrm *PACKAGECONFIG*
- weston-init: fix init code indentation
- weston-init: remove misleading comment about udev rule
- wic: bootimg-partition: Fix file name in debug message
- wic: fix wrong attempt to create file system in upartitioned regions
- wireless-regdb: upgrade to 2023.09.01
- xz: upgrade to 5.4.4
- yocto-uninative: Update to 4.2 for glibc 2.38
- yocto-uninative: Update to 4.3

#### Known Issues in Yocto-4.2.4

- N/A

#### Contributors to Yocto-4.2.4

- Alberto Planas
- Alexander Kanavin
- Alexis Lothoré
- Antoine Lubineau
- Anuj Mittal
- Archana Polampalli
- Arne Schwerdt

- BELHADJ SALEM Talel
- Benjamin Bara
- Bruce Ashfield
- Chen Qi
- Colin McAllister
- Daniel Semkowicz
- Dmitry Baryshkov
- Eilís 'pidge' Ní Fhlannagáin
- Emil Kronborg Andersen
- Etienne Cordonnier
- Jaeyoon Jung
- Jan Garcia
- Joe Slater
- Joshua Watt
- Julien Stephan
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Markus Niebel
- Markus Volk
- Marta Rybczynska
- Martijn de Gouw
- Martin Jansa
- Michael Halstead
- Michael Opdenacker
- Mikko Rapeli
- Mingli Yu
- Narpat Mali
- Otavio Salvador
- Ovidiu Panait
- Peter Kjellerstedt
- Peter Marko

- Peter Suti
- Poonam Jadhav
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Roland Hieber
- Ross Burton
- Ryan Eatmon
- Sakib Sajal
- Samantha Jalabert
- Sanjana
- Sanjay Chitroda
- Sean Nyekjaer
- Siddharth Doshi
- Soumya Sambu
- Stefan Tauner
- Steve Sakoman
- Tan Wen Yan
- Tom Hochstein
- Trevor Gamblin
- Vijay Anusuri
- Wang Mingyu
- Xiangyu Chen
- Yash Shinde
- Yoann Congal
- Yogita Urade
- Yuta Hayama

## Repositories / Downloads for Yocto-4.2.4

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [mickledore](#)
- Tag: [yocto-4.2.4](#)

- Git Revision: [7235399a86b134e57d5eb783d7f1f57ca0439ae5](#)
- Release Artefact: [poky-7235399a86b134e57d5eb783d7f1f57ca0439ae5](#)
- sha: [3d56bb4232ab29ae18249529856f0e638c50c764fc495d6beb1ecd295fa5e5e3](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.4/poky-7235399a86b134e57d5eb783d7f1f57ca0439ae5.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.4/poky-7235399a86b134e57d5eb783d7f1f57ca0439ae5.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [mickledore](#)
- Tag: [yocto-4.2.4](#)
- Git Revision: [23b5141400b2c676c806df3308f023f7c04e34e0](#)
- Release Artefact: [oecore-23b5141400b2c676c806df3308f023f7c04e34e0](#)
- sha: [152f4ee3cdd2e159f6bd34b01d517de44dfe670d35a5e3c84cc32ee7842d9741](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.4/oecore-23b5141400b2c676c806df3308f023f7c04e34e0.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.4/oecore-23b5141400b2c676c806df3308f023f7c04e34e0.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [mickledore](#)
- Tag: [yocto-4.2.4](#)
- Git Revision: [d87d4f00b9c6068fff03929a4b0f231a942d3873](#)
- Release Artefact: [meta-mingw-d87d4f00b9c6068fff03929a4b0f231a942d3873](#)
- sha: [8036847cf5bf3da9db4bad13aac9080d559848679f0ae03694d55a576bcaf75f](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.4/meta-mingw-d87d4f00b9c6068fff03929a4b0f231a942d3873.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.4/meta-mingw-d87d4f00b9c6068fff03929a4b0f231a942d3873.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.4](#)
- Tag: [yocto-4.2.4](#)
- Git Revision: [c7e094ec3beccef0bbbf67c100147c449d9c6836](#)
- Release Artefact: [bitbake-c7e094ec3beccef0bbbf67c100147c449d9c6836](#)
- sha: [6a35a62bee3446cd0f9e0ec1de9b8f60fc396109075b37d7c4a1f2e6d63271c6](#)

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.2.4/bitbake-c7e094ec3beccef0bbbf67c100147c449d9c6836.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.2.4/bitbake-c7e094ec3beccef0bbbf67c100147c449d9c6836.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `mickledore`
- Tag: `yocto-4.2.4`
- Git Revision: `91a29ca94314c87fd3dc68601cd4932bdffde35`

## 17.10 Release 4.1 (langdale)

### 17.10.1 Release 4.1 (langdale)

#### Migration notes for 4.1 (langdale)

This section provides migration information for moving to the Yocto Project 4.1 Release (codename "langdale") from the prior release.

#### **make 4.0 is now the minimum required make version**

glibc now requires `make` 4.0 to build, thus it is now the version required to be installed on the build host. A new *buildtools-make* tarball has been introduced to provide just `make` 4.0 for host distros without a current/working `make` 4.x version; if you also need other tools you can use the updated *buildtools* tarball. For more information see *Pacchetti Richiesti per l'Host di Build*.

#### **Complementary package installation ignores recommends**

When installing complementary packages (e.g. `-dev` and `-dbg` packages when building an SDK, or if you have added `dev-deps` to *IMAGE\_FEATURES*), `recommends` (as defined by *RRECOMMENDS*) are no longer installed.

If you wish to double-check the contents of your images after this change, see *Checking Image / SDK Changes*. If needed you can explicitly install items by adding them to *IMAGE\_INSTALL* in image recipes or *TOOLCHAIN\_TARGET\_TASK* for the SDK.

#### **dev dependencies are now recommends**

The default for `${PN}-dev` package is now to use *RRECOMMENDS* instead of *RDEPENDS* to pull in the main package. This takes advantage of a change to complimentary package installation to not follow *RRECOMMENDS* (as mentioned above) and for example means an SDK for an image with both `openssh` and `dropbear` components will now build successfully.

## dropbear now recommends openssh-sftp-server

openssh has switched the scp client to use the sftp protocol instead of scp to move files. This means scp from Fedora 36 and other current distributions will no longer be able to move files to/from a system running dropbear with no sftp server installed.

The sftp server from openssh is small (200kb uncompressed) and standalone, so adding it to the packagegroup seems to be the best way to preserve the functionality for user sanity. However, if you wish to avoid this dependency, you can either:

- A. Use `dropbear` in *IMAGE\_INSTALL* instead of `packagegroup-core-ssh-dropbear` (or `ssh-server-dropbear` in *IMAGE\_FEATURES*), or
- B. Add `openssh-sftp-server` to *BAD\_RECOMMENDATIONS*.

## Classes now split by usage context

A split directory structure has now been set up for `.bbclass` files - classes that are intended to be inherited only by recipes (e.g. `inherit` in a recipe file, *IMAGE\_CLASSES* or *KERNEL\_CLASSES*) should be in a `classes-recipe` subdirectory and classes that are intended to be inherited globally (e.g. via `INHERIT +=`, *PAC-KAGE\_CLASSES*, *USER\_CLASSES* or *INHERIT\_DISTRO*) should be in `classes-global`. Classes in the existing `classes` subdirectory will continue to work in any context as before.

Other than knowing where to look when manually browsing the class files, this is not likely to require any changes to your configuration. However, if in your configuration you were using some classes in the incorrect context, you will now receive an error during parsing. For example, the following in *build/conf/local.conf* will now cause an error:

```
INHERIT += "testimage"
```

Since *testimage* is a class intended solely to affect image recipes, this would be correctly specified as:

```
IMAGE_CLASSES += "testimage"
```

## Missing local files in SRC\_URI now triggers an error

If a file referenced in *SRC\_URI* does not exist, in 4.1 this will trigger an error at parse time where previously this only triggered a warning. In the past you could ignore these warnings for example if you have multiple build configurations (e.g. for several different target machines) and there were recipes that you were not building in one of the configurations. If you have this scenario you will now need to conditionally add entries to *SRC\_URI* where they are valid, or use *COMPATIBLE\_MACHINE* / *COMPATIBLE\_HOST* to prevent the recipe from being available (and therefore avoid it being parsed) in configurations where the files aren't available.

## QA check changes

- The *buildpaths* QA check is now enabled by default in *WARN\_QA*, and thus any build system paths found in output files will trigger a warning. If you see these warnings for your own recipes, for full binary reproducibility you should make the necessary changes to the recipe build to remove these paths. If you wish to disable the warning for a particular recipe you can use *INSANE\_SKIP*, or for the entire build you can adjust *WARN\_QA*. For more information, see the *buildpaths QA check* section.



- `do_qa_staging` now checks shebang length in all directories specified by `SYSROOT_DIRS`, since there is a maximum length defined in the kernel. For native recipes which write scripts to the sysroot, if the shebang line in one of these scripts is too long you will get an error. This can be skipped using `INSANE_SKIP` if necessary, but the best course of action is of course to fix the script. There is now also a `create_cmdline_shebang_wrapper` function that you can call e.g. from `do_install` (or `do_install:append`) within a recipe to create a wrapper to fix such scripts - see the `libcheck` recipe for an example usage.

## Miscellaneous changes

- `mount.blacklist` has been renamed to `mount.ignorelist` in `udev-extraconf`. If you are customising this file via `udev-extraconf` then you will need to update your `udev-extraconf.bbappend` as appropriate.
- `help2man-native` has been removed from implicit sysroot dependencies. If a recipe needs `help2man-native` it should now be explicitly added to `DEPENDS` within the recipe.
- For images using `systemd`, the reboot watchdog timeout has been set to 60 seconds (from the upstream default of 10 minutes). If you wish to override this you can set `WATCHDOG_TIMEOUT` to the desired timeout in seconds. Note that the same `WATCHDOG_TIMEOUT` variable also specifies the timeout used for the `watchdog` tool (if that is being built).
- The `image-buildinfo` class now writes to `${sysconfdir}/buildinfo` instead of `${sysconfdir}/build` by default (i.e. the default value of `IMAGE_BUILDINFO_FILE` has been changed). If you have code that reads this from images at build or runtime you will need to update it or specify your own value for `IMAGE_BUILDINFO_FILE`.
- In the `archiver` class, the default `ARCHIVER_OUTDIR` value no longer includes the `MACHINE` value in order to avoid the archive task running multiple times in a multiconfig setup. If you have custom code that does something with the files archived by the `archiver` class then you may need to adjust it to the new structure.
- If you are not using `systemd` then `udev` is now configured to use labels (`LABEL` or `PARTLABEL`) to set the mount point for the device. For example:

```
/run/media/rootfs-sda2
```

instead of:

```
/run/media/sda2
```

- `icu` no longer provides the `icu-config` configuration tool - upstream have indicated `icu-config` is deprecated and should no longer be used. Code with references to it will need to be updated, for example to use `pkg-config` instead.
- The `rng-tools` `systemd` service name has changed from `rngd` to `rng-tools`
- The `largefile` `DISTRO_FEATURES` item has been removed, large file support is now always enabled where it was previously optional.
- The Python `zoneinfo` module is now split out to its own `python3-zoneinfo` package.

- The *PACKAGECONFIG* option to enable `wpa_supplicant` in the `connman` recipe has been renamed to "wpa-supPLICANT". If you have set *PACKAGECONFIG* for the `connman` recipe to include this option you will need to update your configuration. Related to this, the *WIRELESS\_DAEMON* variable now expects the new `wpa-supPLICANT` naming and affects `packagegroup-base` as well as `connman`.
- The `wpa-supPLICANT` recipe no longer uses a static (and stale) `defconfig` file, instead it uses the upstream version with appropriate edits for the *PACKAGECONFIG*. If you are customising this file you will need to update your customisations.
- With the introduction of `picobuild` in *python\_pep517*, The `PEP517_BUILD_API` variable is no longer supported. If you have any references to this variable you should remove them.

## Removed recipes

The following recipes have been removed in this release:

- `alsa-utils-scripts`: merged into `alsa-utils`
- `cargo-cross-canadian`: optimised out
- `lzop`: obsolete, unmaintained upstream
- `linux-yocto (5.10)`: 5.15 and 5.19 are currently provided
- `rust-cross`: optimised out
- `rust-crosssdk`: optimised out
- `rust-tools-cross-canadian`: optimised out
- `xf86-input-keyboard`: obsolete (replaced by `libinput/evdev`)

## 17.10.2 Release notes for 4.1 (langdale)

### New Features / Enhancements in 4.1

- Linux kernel 5.19, glibc 2.36 and ~260 other recipe upgrades
- `make` 4.0 is now the minimum `make` version required on the build host. For host distros that do not provide it, this is included as part of the *buildtools* tarball, and additionally a new *buildtools-make* tarball has been introduced to provide this in particular for host distros with a broken `make` 4.x version. For more details see *Versioni richieste di Git, tar, Python, make e gcc*.
- New layer setup tooling:
  - New `scripts/oe-setup-layers` standalone script to restore the layer configuration from a json file
  - New `bitbake-layers create-layers-setup` command to save the layer configuration to a json file
  - New `bitbake-layers save-build-conf` command to save the active build configuration as a template into a layer
- Rust-related enhancements:
  - Support for building rust for the target

- Significant SDK toolchain build optimisation
- Support for building native components in the SDK
- Support `crate://` fetcher with *externalsrc*
- New core recipes:
  - `buildtools-make-tarball`
  - `icon-naming-utils` (previously removed)
  - `musl-locales`
  - `python3-editables` (originally in meta-python)
  - `python3-hatch-vcs`
  - `python3-hatchling` (originally in meta-oe)
  - `python3-lxml` (originally in meta-python)
  - `python3-pathspect` (originally in meta-python)
  - `python3-picobuild`
  - `sato-icon-theme` (previously removed)
- CVE checking enhancements:
  - New `CVE_DB_UPDATE_INTERVAL` variable to allow specifying the CVE database minimum update interval (and default to once per day)
  - Added JSON format to summary output
  - Added support for Ignored CVEs
  - Enable recursive CVE checking also for `do_populate_sdk`
  - New `CVE_CHECK_SHOW_WARNINGS` variable to disable unpatched CVE warning messages
  - The *pypi* class now defaults *CVE\_PRODUCT* from *PYPI\_PACKAGE*
  - Added current kernel CVEs to ignore list since we stay as close to the kernel stable releases as we can
  - Optimisations to avoid dependencies on fetching
- Complementary package installation (as used in SDKs and images) no longer installs recommended packages, in order to avoid conflicts
- Dependency of `-dev` package on main package is now an *RRECOMMENDS* and can be easily set via new *DEV\_PKG\_DEPENDENCY* variable
- Support for CPU, I/O and memory pressure regulation in BitBake
- Pressure data gathering in *buildstats* and rendering in *pybootchartgui*
- New Picobuild system for lightweight Python PEP-517 build support in the *python\_pep517* class
- Many classes are now split into global and recipe contexts for better validation. For more information, see *Classes now split by usage context*.
- Architecture-specific enhancements:

- arch-armv8-4a.inc: add tune include for armv8.4a
- tune-neoversen2: support tune-neoversen2 base on armv9a
- riscv: Add tunes for rv64 without compressed instructions
- gnu-efi: enable for riscv64
- shadow-securetty: allow ttyS4 for amd-snowyowl-64
- Kernel-related enhancements:
  - linux-yocto/5.15: cfg/xen: Move x86 configs to separate file
  - linux-yocto/5.15: Enabled MDIO bus config
  - linux-yocto: Enable mdio for qemu
  - linux-yocto/5.15: base: enable kernel crypto userspace API
  - kern-tools: allow 'y' or 'm' to avoid config audit warnings
  - kernel-yocto.bbclass: say what *SRC\_URI* entry is being dropped
  - kernel.bbclass: Do not overwrite recipe's custom postinst
  - kmod: Enable xz support by default
  - Run depmod(wrapper) against each compiled kernel when multiple kernels are enabled
  - linux-yocto-tiny: enable qemuarmv5/qemuarm64
- wic Image Creator enhancements:
  - Added dependencies to support erofs
  - Added `fspassno` parameter to partition to allow specifying the value of the last column (`fs_passno`) in `/etc/fstab`.
  - bootimg-efi: added support for loading devicetree files
  - Added `none` fstype for custom image (for use in conjunction with `rawcopy`)
- SDK-related enhancements:
  - *Support for using the regular build system as an SDK*
  - *image-buildinfo* class now also writes build information to SDKs
  - New `SDK_TOOLCHAIN_LANGS` variable to control support of rust / go in SDK
  - rust-llvm: enabled *nativesdk* variant
  - python3-pluggy: enabled for *native* / *nativesdk*
- QEMU/runqemu enhancements:
  - qemu86-64: Allow higher tunes
  - runqemu: display host uptime when starting
  - runqemu: add `QB_KERNEL_CMDLINE` that can be set to "none" to avoid overriding kernel command line specified in dtb

- Image-related enhancements:
  - New variable `UBOOT_MKIMAGE_KERNEL_TYPE`
  - New variable `FIT_PAD_ALG` to control FIT image padding algorithm
  - New `KERNEL_DEPLOY_DEPEND` variable to allow disabling image dependency on deploying the kernel
  - `image_types`: isolate the write of UBI configuration to a `write_ubi_config` function that can be easily overridden
- openssh: add support for config snippet includes to ssh and sshd
- `create-spdx`: Add `SPDX_PRETTY` option
- wpa-supPLICant: build static library if not disabled via `DISABLE_STATIC`
- wpa-supPLICant: package dynamic modules
- openssl: extract legacy provider module to a separate package
- linux-firmware: split out ath3k firmware
- linux-firmware: add support for building snapshots
- eudev: create static-nodes in init script
- udev-extraconf: new `MOUNT_BASE` variable allows configuring automount base directory
- udev-extraconf/mount.sh: use partition labels in mountpoint paths
- systemd: Set RebootWatchdogSec to 60s by default
- systemd: systemd-systemctl: Support instance conf files during enable
- weston.init: enable `xwayland` in `weston.ini` if `x11` is in `DISTRO_FEATURES`
- New `npm_registry` Python module to enable caching with nodejs 16+
- `npm`: replaced `npm pack` call with `tar czf` for nodejs 16+ compatibility and improved `do_configure` performance
- Enabled `bin_package` class to work properly in the native case
- Enabled `buildpaths` QA check as a warning by default
- New `OVERLAYFS_ETC_EXPOSE_LOWER` to provide read-only access to the original `/etc` content with `overlayfs-etc`
- New `OVERLAYFS_QA_SKIP` variable to allow skipping check on `overlayfs` mounts
- New `PACKAGECONFIG` options for individual recipes:
  - apr: xsi-strerror
  - btrfs-tools: lzo
  - connman: iwd
  - coreutils: openssl
  - dropbear: enable-x11-forwarding

- eudev: blkid, kmod, rule-generator
  - eudev: manpages, selinux
  - flac: avx, ogg
  - gnutls: fips
  - gstreamer1.0-plugins-bad: avtp
  - libsd12: libusb
  - llvm: optviewer
  - mesa: vulkan, vulkan-beta, zink
  - perf: bfd
  - piglit: glx, opengl
  - python3: editline
  - qemu: bpf, brlapi, capstone, rdma, slirp, uring, vde
  - rpm: readline
  - ruby: capstone
  - systemd: no-dns-fallback, sysext
  - tiff: jbig
- ptest enhancements in `curl`, `json-c`, `libgcrypt`, `libgpg-error`, `libxml2`
  - ptest compile/install functions now use `PARALLEL_MAKE` and `PARALLEL_MAKEINST` in ptest for significant speedup
  - New `TC_CXX_RUNTIME` variable to enable other layers to more easily control C++ runtime
  - Set `BB_DEFAULT_UMASK` using `??=` to make it easier to override
  - Set `TCLIBC` and `TCMODE` using `??=` to make them easier to override
  - squashfs-tools: build with lzo support by default
  - insane.bbclass: make `do_qa_staging` check shebang length for native scripts in all `SYSROOT_DIRS`
  - utils: Add `create_cmdline_shebang_wrapper` function to allow recipes to easily create a wrapper to fix long shebang lines
  - meson: provide relocation script and native/cross wrappers also for meson-native
  - meson.bbclass: add cython binary to cross/native toolchain config
  - New `musl-locales` recipe to provide a limited set of locale data for musl based systems
  - gobject-introspection: use `OBJDUMP` environment variable so that objdump tool can be picked up from the environment
  - The Python `zoneinfo` module is now split out to its own `python3-zoneinfo` package.
  - busybox: added devmem 128-bit support

- vim: split xxd out into its own package
- New *github-releases* class to consolidate version checks for github-based packages
- `devtool reset` now preserves `workspace/sources` source trees in `workspace/attic/sources/` instead of leaving them in-place
- `scripts/patchreview`: Add commit to stored json data
- `scripts/patchreview`: Make json output human parsable
- `wpa-supPLICANT` recipe now uses the upstream `defconfig` modified based upon *PACKAGECONFIG* instead of a stale `defconfig` file
- `bitbake: build`: prefix the tasks with a timestamp in the `log.task_order`
- `bitbake: fetch2/osc`: Add support to query latest revision
- `bitbake: utils`: Pass lock argument in `fileslocked`
- `bitbake: utils`: Add `enable_loopback_networking()`

### Known Issues in 4.1

- The change to *Complementary package installation ignores recommends* means that images built with the `ptest-pkgs IMAGE_FEATURES` don't automatically install `ptest-runner`, as that package is a recommendation of the individual `-ptest` packages. This will be resolved in the next point release, and can be worked around by explicitly installing `ptest-runner` into the image. Filed as [bug 14928](#).
- There is a known issue with eSDKs where sstate objects may be missing, resulting in packages being unavailable to install in the sysroot. This is due to image generation optimisations having unintended consequences in eSDK generation. This will be resolved in the next point release. Filed as [bug 14626](#), which also details the fix.
- The change to *Classes now split by usage context* inadvertently moved the *externalsrc* class to `meta/classes-recipe`, when it is not recipe-specific and can also be used in a global context. The class will be moved back to `meta/classes` in the next point release. Filed as [bug 14940](#).

### Recipe License changes in 4.1

The following corrections have been made to the *LICENSE* values set by recipes:

- `alsa-state`: add GPL-2.0-or-later because of `alsa-state-init` file
- `git`: add GPL-2.0-or-later & BSD-3-Clause & MIT & BSL-1.0 & LGPL-2.1-or-later due to embedded code
- `libgcrypt`: dropped GPLv3 license after upstream changes
- `linux-firmware`: correct license for ar3k firmware (specific "ar3k" license)

### Security Fixes in 4.1

- `bind`: CVE-2022-1183, CVE-2022-2795, CVE-2022-2881, CVE-2022-2906, CVE-2022-3080, CVE-2022-38178
- `binutils`: CVE-2019-1010204, CVE-2022-38126, CVE-2022-38127, CVE-2022-38128, CVE-2022-38533
- `busybox`: CVE-2022-30065

- connman: CVE-2022-32292, CVE-2022-32293
- cups: CVE-2022-26691
- e2fsprogs: CVE-2022-1304
- expat: CVE-2022-40674
- freetype: CVE-2022-27404
- glibc: CVE-2022-39046
- gnupg: CVE-2022-34903
- grub2: CVE-2021-3695, CVE-2021-3696, CVE-2021-3697, CVE-2022-28733, CVE-2022-28734, CVE-2022-28735
- inetutils: CVE-2022-39028
- libtirpc: CVE-2021-46828
- libxml2: CVE-2016-3709 (ignored)
- libxslt: CVE-2022-29824 (not applicable)
- linux-yocto/5.15: CVE-2022-28796
- logrotate: CVE-2022-1348
- lua: CVE-2022-33099
- nasm: CVE-2020-18974 (ignored)
- ncurses: CVE-2022-29458
- openssl: CVE-2022-1292, CVE-2022-1343, CVE-2022-1434, CVE-2022-1473, CVE-2022-2068, CVE-2022-2274, CVE-2022-2097
- python3: CVE-2015-20107 (ignored)
- qemu: CVE-2021-20255 (ignored), CVE-2019-12067 (ignored), CVE-2021-3507, CVE-2022-0216, CVE-2022-2962, CVE-2022-35414
- rpm: CVE-2021-35937, CVE-2021-35938, CVE-2021-35939
- rsync: CVE-2022-29154
- subversion: CVE-2021-28544, CVE-2022-24070
- tiff: CVE-2022-1210 (not applicable), CVE-2022-1622, CVE-2022-1623 (invalid), CVE-2022-2056, CVE-2022-2057, CVE-2022-2058, CVE-2022-2953, CVE-2022-34526
- unzip: CVE-2022-0529, CVE-2022-0530
- vim: CVE-2022-1381, CVE-2022-1420, CVE-2022-1621, CVE-2022-1629, CVE-2022-1674, CVE-2022-1733, CVE-2022-1735, CVE-2022-1769, CVE-2022-1771, CVE-2022-1785, CVE-2022-1796, CVE-2022-1927, CVE-2022-1942, CVE-2022-2257, CVE-2022-2264, CVE-2022-2284, CVE-2022-2285, CVE-2022-2286, CVE-2022-2287, CVE-2022-2816, CVE-2022-2817, CVE-2022-2819, CVE-2022-2845, CVE-2022-2849, CVE-2022-2862, CVE-2022-2874, CVE-2022-2889, CVE-2022-2980, CVE-2022-2946, CVE-2022-2982, CVE-2022-3099, CVE-2022-3134, CVE-2022-3234, CVE-2022-3278



- [zlib: CVE-2022-37434](#)

## Recipe Upgrades in 4.1

- [acpica 20211217 -> 20220331](#)
- [adwaita-icon-theme 41.0 -> 42.0](#)
- [alsa-lib 1.2.6.1 -> 1.2.7.2](#)
- [alsa-plugins 1.2.6 -> 1.2.7.1](#)
- [alsa-ucm-conf 1.2.6.3 -> 1.2.7.2](#)
- [alsa-utils 1.2.6 -> 1.2.7](#)
- [asciidoc 10.1.4 -> 10.2.0](#)
- [at-spi2-core 2.42.0 -> 2.44.1](#)
- [autoconf-archive 2022.02.11 -> 2022.09.03](#)
- [base-passwd 3.5.29 -> 3.5.52](#)
- [bind 9.18.5 -> 9.18.7](#)
- [binutils 2.38 -> 2.39](#)
- [boost 1.78.0 -> 1.80.0](#)
- [boost-build-native 4.4.1 -> 1.80.0](#)
- [btrfs-tools 5.16.2 -> 5.19.1](#)
- [cargo 1.59.0 -> 1.63.0](#)
- [ccache 4.6 -> 4.6.3](#)
- [cmake 3.22.3 -> 3.24.0](#)
- [cmake-native 3.22.3 -> 3.24.0](#)
- [coreutils 9.0 -> 9.1](#)
- [createrepo-c 0.19.0 -> 0.20.1](#)
- [cross-localedef-native 2.35 -> 2.36](#)
- [curl 7.82.0 -> 7.85.0](#)
- [diffoscope 208 -> 221](#)
- [dmidecode 3.3 -> 3.4](#)
- [dnf 4.11.1 -> 4.14.0](#)
- [dos2unix 7.4.2 -> 7.4.3](#)
- [dpkg 1.21.4 -> 1.21.9](#)
- [dropbear 2020.81 -> 2022.82](#)
- [efibootmgr 17 -> 18](#)

- elfutils 0.186 -> 0.187
- ell 0.50 -> 0.53
- enchant2 2.3.2 -> 2.3.3
- erofs-utils 1.4 -> 1.5
- ethtool 5.16 -> 5.19
- eudev 3.2.10 -> 3.2.11
- ffmpeg 5.0.1 -> 5.1.1
- file 5.41 -> 5.43
- flac 1.3.4 -> 1.4.0
- fontconfig 2.13.1 -> 2.14.0
- freetype 2.11.1 -> 2.12.1
- gcc 11.3.0 -> 12.2.0
- gcompat 1.0.0+1.1+gitX (4d6a5156a6eb...) -> 1.0.0+1.1+gitX (c6921a1aa454...)
- gdb 11.2 -> 12.1
- ghostscript 9.55.0 -> 9.56.1
- git 2.35.4 -> 2.37.3
- glibc 2.35 -> 2.36
- glslang 1.3.204.1 -> 1.3.216.0
- gnu-config 20211108+gitX -> 20220525+gitX
- gnu-efi 3.0.14 -> 3.0.15
- gnutls 3.7.4 -> 3.7.7
- go 1.17.13 -> 1.19
- go-helloworld 0.1 (787a929d5a0d...) -> 0.1 (2e68773dfca0...)
- gpgme 1.17.1 -> 1.18.0
- gptfdisk 1.0.8 -> 1.0.9
- harfbuzz 4.0.1 -> 5.1.0
- hdparm 9.63 -> 9.64
- help2man 1.49.1 -> 1.49.2
- hwlatdetect 2.3 -> 2.4
- icu 70.1 -> 71.1
- inetutils 2.2 -> 2.3
- init-system-helpers 1.62 -> 1.64

- iproute2 5.17.0 -> 5.19.0
- iptables 1.8.7 -> 1.8.8
- iw 5.16 -> 5.19
- json-c 0.15 -> 0.16
- kbd 2.4.0 -> 2.5.1
- kea 2.0.2 -> 2.2.0
- kexec-tools 2.0.23 -> 2.0.25
- kmod 29 -> 30
- kmscube git (9f63f359fab1...) -> git (3bf6ee1a0233...)
- less 600 -> 608
- libaio 0.3.112 -> 0.3.113
- libbsd 0.11.5 -> 0.11.6
- libcap-ng 0.8.2 -> 0.8.3
- libcap-ng-python 0.8.2 -> 0.8.3
- libcgrouper 2.0.2 -> 3.0.0
- libcomps 0.1.18 -> 0.1.19
- libdnf 0.66.0 -> 0.69.0
- libdrm 2.4.110 -> 2.4.113
- libevdev 1.12.1 -> 1.13.0
- libfontenc 1.1.4 -> 1.1.6
- libgcc 11.3.0 -> 12.2.0
- libgcc-initial 11.3.0 -> 12.2.0
- libgcrypt 1.9.4 -> 1.10.1
- libgfortran 11.3.0 -> 12.2.0
- libgit2 1.4.3 -> 1.5.0
- libgpg-error 1.44 -> 1.45
- libhandy 1.5.0 -> 1.6.3
- libidn2 2.3.2 -> 2.3.3
- libjitterentropy 3.4.0 -> 3.4.1
- libmnl 1.0.4 -> 1.0.5
- libnl 3.5.0 -> 3.7.0
- libnotify 0.7.9 -> 0.8.1

- libpipeline 1.5.5 -> 1.5.6
- libproxy 0.4.17 -> 0.4.18
- librepo 1.14.3 -> 1.14.5
- librsvg 2.52.7 -> 2.54.5
- libSDL2 2.0.20 -> 2.24.0
- libseccomp 2.5.3 -> 2.5.4
- libsndfile1 1.0.31 -> 1.1.0
- libstd-rs 1.59.0 -> 1.63.0
- libtirpc 1.3.2 -> 1.3.3
- libubootenv 0.3.2 -> 0.3.3
- libva 2.14.0 -> 2.15.0
- libva-utils 2.14.0 -> 2.15.0
- libx11 1.7.3.1 -> 1.8.1
- libxau 1.0.9 -> 1.0.10
- libxcb 1.14 -> 1.15
- libxcursor 1.2.0 -> 1.2.1
- libxcvt 0.1.1 -> 0.1.2
- libxfont2 2.0.5 -> 2.0.6
- libxvmc 1.0.12 -> 1.0.13
- linux-libc-headers 5.16 -> 5.19
- linux-yocto 5.10.143+gitX, 5.15.68+gitX -> 5.15.68+gitX, 5.19.9+gitX
- linux-yocto-dev 5.18++gitX -> 5.19++gitX
- linux-yocto-rt 5.10.143+gitX, 5.15.68+gitX -> 5.15.68+gitX, 5.19.9+gitX
- linux-yocto-tiny 5.10.143+gitX, 5.15.68+gitX -> 5.15.68+gitX, 5.19.9+gitX
- llvm 13.0.1 -> 14.0.6
- lsof 4.94.0 -> 4.95.0
- ltp 20220121 -> 20220527
- ltng-tools 2.13.4 -> 2.13.8
- ltng-ust 2.13.3 -> 2.13.4
- mc 4.8.27 -> 4.8.28
- mesa 22.0.3 -> 22.2.0
- mesa-demos 8.4.0 -> 8.5.0

- mesa-gl 22.0.3 -> 22.2.0
- meson 0.61.3 -> 0.63.2
- mmc-utils 0.1+gitX (b7e4d5a6ae99...) -> 0.1+gitX (d7b343fd2628...)
- mpg123 1.29.3 -> 1.30.2
- msmtmp 1.8.20 -> 1.8.22
- mtools 4.0.38 -> 4.0.40
- musl 1.2.3+gitX (7a43f6fea908...) -> 1.2.3+gitX (37e18b7bf307...)
- musl-obstack 1.1 -> 1.2
- ncurses 6.3+20220423 (a0bc708bc695...) -> 6.3+20220423 (20db1fb41ec9...)
- neard 0.16 -> 0.18
- nettle 3.7.3 -> 3.8.1
- nfs-utils 2.6.1 -> 2.6.2
- nhttp2 1.47.0 -> 1.49.0
- ninja 1.10.2 -> 1.11.1
- numactl 2.0.14 -> 2.0.15
- ofono 1.34 -> 2.0
- opensbi 1.0 -> 1.1
- openssh 8.9p1 -> 9.0p1
- opkg 0.5.0 -> 0.6.0
- ovmf edk2-stable202202 -> edk2-stable202205
- pango 1.50.4 -> 1.50.9
- parted 3.4 -> 3.5
- patchelf 0.14.5 -> 0.15.0
- pciutils 3.7.0 -> 3.8.0
- perl 5.34.1 -> 5.36.0
- perlcross 1.3.7 -> 1.4
- piglit 1.0+gitX (2f80c7cc9c02...) -> 1.0+gitX (265896c86f90...)
- pkgconf 1.8.0 -> 1.9.3
- psmisc 23.4 -> 23.5
- pulseaudio 15.0 -> 16.1
- puzzles 0.0+gitX (c43a34fbfe43...) -> 0.0+gitX (8399cff6a3b9...)
- python3 3.10.4 -> 3.10.6

- python3-atomicwrites 1.4.0 -> 1.4.1
- python3-attrs 21.4.0 -> 22.1.0
- python3-babel 2.9.1 -> 2.10.3
- python3-bcrypt 3.2.0 -> 3.2.2
- python3-certifi 2021.10.8 -> 2022.9.14
- python3-cffi 1.15.0 -> 1.15.1
- python3-chardet 4.0.0 -> 5.0.0
- python3-cryptography 36.0.2 -> 37.0.4
- python3-cryptography-vectors 36.0.2 -> 37.0.4
- python3-cython 0.29.28 -> 0.29.32
- python3-dbusmock 0.27.3 -> 0.28.4
- python3-docutils 0.18.1 -> 0.19
- python3-dtschema 2022.1 -> 2022.8.3
- python3-hypothesis 6.39.5 -> 6.54.5
- python3-idna 3.3 -> 3.4
- python3-imagesize 1.3.0 -> 1.4.1
- python3-importlib-metadata 4.11.3 -> 4.12.0
- python3-jinja2 3.1.1 -> 3.1.2
- python3-jsonpointer 2.2 -> 2.3
- python3-jsonschema 4.4.0 -> 4.9.1
- python3-magic 0.4.25 -> 0.4.27
- python3-mako 1.1.6 -> 1.2.2
- python3-markdown 3.3.6 -> 3.4.1
- python3-more-itertools 8.12.0 -> 8.14.0
- python3-numpy 1.22.3 -> 1.23.3
- python3-pbr 5.8.1 -> 5.10.0
- python3-pip 22.0.3 -> 22.2.2
- python3-psutil 5.9.0 -> 5.9.2
- python3-pycryptodome 3.14.1 -> 3.15.0
- python3-pycryptodomex 3.14.1 -> 3.15.0
- python3-pyelftools 0.28 -> 0.29
- python3-pygments 2.11.2 -> 2.13.0

- python3-pyobject 3.42.0 -> 3.42.2
- python3-pyparsing 3.0.7 -> 3.0.9
- python3-pytest 7.1.1 -> 7.1.3
- python3-pytest-subtests 0.7.0 -> 0.8.0
- python3-pytz 2022.1 -> 2022.2.1
- python3-requests 2.27.1 -> 2.28.1
- python3-scons 4.3.0 -> 4.4.0
- python3-semantic-version 2.9.0 -> 2.10.0
- python3-setuptools 59.5.0 -> 65.0.2
- python3-setuptools-scm 6.4.2 -> 7.0.5
- python3-sphinx 4.4.0 -> 5.1.1
- python3-sphinx-rtd-theme 0.5.0 -> 1.0.0
- python3-typing-extensions 3.10.0.0 -> 4.3.0
- python3-urllib3 1.26.9 -> 1.26.12
- python3-webcolors 1.11.1 -> 1.12
- python3-zipp 3.7.0 -> 3.8.1
- qemu 6.2.0 -> 7.1.0
- repo 2.22 -> 2.29.2
- rpm 4.17.0 -> 4.18.0
- rsync 3.2.3 -> 3.2.5
- rt-tests 2.3 -> 2.4
- rust 1.59.0 -> 1.63.0
- rust-llvm 1.59.0 -> 1.63.0
- sbc 1.5 -> 2.0
- seatd 0.6.4 -> 0.7.0
- shaderc 2022.1 -> 2022.2
- shadow 4.11.1 -> 4.12.1
- shared-mime-info 2.1 -> 2.2
- slang 2.3.2 -> 2.3.3
- speex 1.2.0 -> 1.2.1
- speexdsp 1.2.0 -> 1.2.1
- spirv-headers 1.3.204.1 -> 1.3.216.0

- spirv-tools 1.3.204.1 -> 1.3.216.0
- sqlite3 3.38.5 -> 3.39.3
- squashfs-tools 4.5 -> 4.5.1
- strace 5.16 -> 5.19
- stress-ng 0.13.12 -> 0.14.03
- sudo 1.9.10 -> 1.9.11p3
- sysklogd 2.3.0 -> 2.4.4
- sysstat 12.4.5 -> 12.6.0
- systemd 250.5 -> 251.4
- systemd-boot 250.5 -> 251.4
- systemtap 4.6 -> 4.7
- systemtap-native 4.6 -> 4.7
- systemtap-uprobes 4.6 -> 4.7
- sysvinit 3.01 -> 3.04
- tiff 4.3.0 -> 4.4.0
- tzcode-native 2022c -> 2022d
- tzdata 2022c -> 2022d
- u-boot 2022.01 -> 2022.07
- u-boot-tools 2022.01 -> 2022.07
- util-linux 2.37.4 -> 2.38.1
- util-linux-libuuid 2.37.4 -> 2.38.1
- valgrind 3.18.1 -> 3.19.0
- vim 9.0.0541 -> 9.0.0598
- vim-tiny 9.0.0541 -> 9.0.0598
- virglrenderer 0.9.1 -> 0.10.3
- vte 0.66.2 -> 0.68.0
- vulkan-headers 1.3.204.1 -> 1.3.216.0
- vulkan-loader 1.3.204.1 -> 1.3.216.0
- vulkan-samples git (28ca2dad83ce...) -> git (74d45aace02d...)
- vulkan-tools 1.3.204.1 -> 1.3.216.0
- wayland 1.20.0 -> 1.21.0
- wayland-protocols 1.25 -> 1.26



- webkitgtk 2.36.5 -> 2.36.7
- x264 r3039+gitX (5db6aa6cab1b...) -> r3039+gitX (baee400fa9ce...)
- xauth 1.1.1 -> 1.1.2
- xcb-proto 1.14.1 -> 1.15.2
- xf86-video-cirrus 1.5.3 -> 1.6.0
- xkeyboard-config 2.35.1 -> 2.36
- xmlto 0.0.28 -> 0.0.28+0.0.29+gitX
- xorgproto 2021.5 -> 2022.2
- zlib 1.2.11 -> 1.2.12

## Contributors to 4.1

Thanks to the following people who contributed to this release:

- Aatir Manzur
- Ahmed Hossam
- Alejandro Hernandez Samaniego
- Alexander Kanavin
- Alexandre Belloni
- Alex Kiernan
- Alex Stewart
- Andrei Gherzan
- Andrej Valek
- Andrey Konovalov
- Aníbal Limón
- Anuj Mittal
- Arkadiusz Drabczyk
- Armin Kuster
- Aryaman Gupta
- Awais Belal
- Beniamin Sandu
- Bertrand Marquis
- Bob Henz
- Bruce Ashfield
- Carlos Rafael Giani

- Changhyeok Bae
- Changqing Li
- Chanho Park
- Chen Qi
- Christoph Lauer
- Claudius Heine
- Daiane Angolini
- Daniel Gomez
- Daniel McGregor
- David Bagonyi
- Davide Gardenal
- Denys Dmytriienko
- Dmitry Baryshkov
- Drew Moseley
- Enrico Scholz
- Ernst Sjöstrand
- Etienne Cordonnier
- Fabio Estevam
- Federico Pellegrin
- Felix Moessbauer
- Ferry Toth
- Florin Diaconescu
- Gennaro Iorio
- Grygorii Tertychnyi
- Gunjan Gupta
- Henning Schild
- He Zhe
- Hitendra Prajapati
- Jack Mitchell
- Jacob Kroon
- Jan Kiszka
- Jan Luebbe

- Jan Vermaete
- Jasper Orschulko
- JeongBong Seo
- Jeremy Puhlman
- Jiaqing Zhao
- Joerg Vehlowl
- Johan Korsnes
- Johannes Schneider
- John Edward Broadbent
- Jon Mason
- Jose Quaresma
- Joshua Watt
- Justin Bronder
- Kai Kang
- Kevin Hao
- Khem Raj
- Konrad Weihmann
- Kory Maincent
- Kristian Amlie
- Lee Chee Yang
- Lei Maohui
- Leon Anavi
- Luca Ceresoli
- Lucas Stach
- LUIS ENRIQUEZ
- Marcel Ziswiler
- Marius Kriegerowski
- Mark Hatle
- Markus Volk
- Marta Rybczynska
- Martin Beeger
- Martin Jansa

- Mateusz Marciniec
- Mattias Jernberg
- Matt Madison
- Maxime Roussin-Bélanger
- Michael Halstead
- Michael Opdenacker
- Mihai Lindner
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Muhammad Hamza
- Naveen Saini
- Neil Horman
- Nick Potenski
- Nicolas Dechesne
- Niko Mauno
- Ola x Nilsson
- Otavio Salvador
- Pascal Bach
- Paul Eggleton
- Paul Gortmaker
- Paulo Neves
- Pavel Zhukov
- Peter Bergin
- Peter Kjellerstedt
- Peter Marko
- Petr Vorel
- Pgowda
- Portia Stephens
- Quentin Schulz
- Rahul Kumar
- Raju Kumar Pothuraju

- Randy MacLeod
- Raphael Teller
- Rasmus Villemoes
- Ricardo Salveti
- Richard Purdie
- Robert Joslyn
- Robert Yang
- Roland Hieber
- Ross Burton
- Rouven Czerwinski
- Ruiqiang Hao
- Russ Dill
- Rusty Howell
- Sakib Sajal
- Samuli Piippo
- Schmidt, Adriaan
- Sean Anderson
- Shruthi Ravichandran
- Shubham Kulkarni
- Simone Weiss
- Sebastian Suesens
- Stefan Herbrechtsmeier
- Stefano Babic
- Stefan Wiehler
- Steve Sakoman
- Sundeep KOKKONDA
- Teoh Jay Shen
- Thomas Epperson
- Thomas Perrot
- Thomas Roos
- Tobias Schmidl
- Tomasz Dziendzielski

- Tom Hochstein
- Tom Rini
- Trevor Woerner
- Ulrich Ölmann
- Vyacheslav Yurkov
- Wang Mingyu
- William A. Kennington III
- Xiaobing Luo
- Xu Huan
- Yang Xu
- Yi Zhao
- Yogesh Tyagi
- Yongxin Liu
- Yue Tao
- Yulong (Kevin) Liu
- Zach Welch
- Zheng Ruoqin
- Zoltán Böszörményi

## Repositories / Downloads for 4.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [langdale](#)
- Tag: [yocto-4.1](#)
- Git Revision: [5200799866b92259e855051112520006e1aaaac0](#)
- Release Artefact: [poky-5200799866b92259e855051112520006e1aaaac0](#)
- sha: [9d9a2f7ecf2502f89f43bf45d63e6b61cdcb95ed1d75c8281372f550d809c823](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1/poky-5200799866b92259e855051112520006e1aaaac0.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.1/poky-5200799866b92259e855051112520006e1aaaac0.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [langdale](#)
- Tag: [yocto-4.1](#)

- Git Revision: [744a2277844ec9a384a9ca7dae2a634d5a0d3590](#)
- Release Artefact: [oecore-744a2277844ec9a384a9ca7dae2a634d5a0d3590](#)
- sha: [34f1fd5bb83514bf0ec8ad7f8cce088a8e28677e1338db94c188283da704c663](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1/oecore-744a2277844ec9a384a9ca7dae2a634d5a0d3590.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1/oecore-744a2277844ec9a384a9ca7dae2a634d5a0d3590.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [langdale](#)
- Tag: [yocto-4.1](#)
- Git Revision: [b0067202db8573df3d23d199f82987cebe1bee2c](#)
- Release Artefact: [meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c](#)
- sha: [704f2940322b81ce774e9cbd27c3cfa843111d497dc7b1eaa39cd694d9a2366](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.2](#)
- Tag: [yocto-4.1](#)
- Git Revision: [074da4c469d1f4177a1c5be72b9f3ccdfd379d67](#)
- Release Artefact: [bitbake-074da4c469d1f4177a1c5be72b9f3ccdfd379d67](#)
- sha: [e32c300e0c8522d8d49ef10aae473bd5f293202672eb9d38e90ed92594ed1fe8](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1/bitbake-074da4c469d1f4177a1c5be72b9f3ccdfd379d67.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1/bitbake-074da4c469d1f4177a1c5be72b9f3ccdfd379d67.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [langdale](#)
- Tag: [yocto-4.1](#)
- Git Revision: [42d3e26a0d04bc5951e640b471686f347dc9b74a](#)

## 17.10.3 Release notes for Yocto-4.1.1 (Langdale)

### Security Fixes in Yocto-4.1.1

- curl: Fix CVE-2022-32221, CVE-2022-35260, CVE-2022-42915 and CVE-2022-42916
- libx11: Fix CVE-2022-3554
- lighttpd: Fix CVE-2022-41556
- openssl: Fix CVE-2022-3358, CVE-2022-3602 and CVE-2022-3786
- pixman: Fix CVE-2022-44638
- qemu: Fix CVE-2022-3165
- sudo: Fix CVE-2022-43995
- tiff: Fix CVE-2022-3599, CVE-2022-3597, CVE-2022-3626, CVE-2022-3627, CVE-2022-3570 and CVE-2022-3598
- xserver-xorg: Fix CVE-2022-3550 and CVE-2022-3551
- xserver-xorg: Ignore CVE-2022-3553

### Fixes in Yocto-4.1.1

- Add 4.1 migration guide & release notes
- bitbake: asynrcpc: serv: correct closed client socket detection
- bitbake: bitbake-user-manual: details about variable flags starting with underscore
- bitbake: bitbake: bitbake-layers: checkout layer(s) branch when clone exists
- bitbake: bitbake: user-manual: inform about spaces in :remove
- bitbake: doc: bitbake-user-manual: expand description of BB\_PRESSURE\_MAX variables
- bitbake: fetch2/git: don't set core.fsycobjectfiles=0
- bitbake: tests/fetch: Allow handling of a file:// url within a submodule
- bitbake: tests: bb.tests.fetch.URLHandle: add 2 new tests
- bitbake: utils/ply: Update md5 to better report errors with hashlib
- bluez5: add dbus to RDEPENDS
- build-appliance-image: Update to langdale head revision
- buildconf: compare abspath
- buildtools-tarball: export certificates to python and curl
- cmake-native: Fix host tool contamination
- create-spdx.bbclass: remove unused SPDX\_INCLUDE\_PACKAGED
- create-spdx: Remove ";name=..." for downloadLocation
- cve-update-db-native: add timeout to urlopen() calls



- dev-manual: common-tasks.rst: add reference to "do\_clean" task
- dev-manual: common-tasks.rst: add reference to "do\_listtasks" task
- docs: add support for langdale (4.1) release
- dropbear: add pam to *PACKAGECONFIG*
- externalsrc.bbclass: fix git repo detection
- externalsrc.bbclass: Remove a trailing slash from \${B}
- externalsrc: move back to classes
- gcc: Allow -Wno-error=poison-system-directories to take effect
- glib-2.0: fix rare GFileInfo test case failure
- gnutls: Unified package names to lower-case
- gnutls: upgrade 3.7.7 -> 3.7.8
- grub: disable build on armv7ve/a with hardfp
- gstreamer1.0-libav: fix errors with ffmpeg 5.x
- ifupdown: upgrade 0.8.37 -> 0.8.39
- insane.bbclass: Allow hashlib version that only accepts one parameter
- install-buildtools: support buildtools-make-tarball and update to 4.1
- kern-tools: fix relative path processing
- kernel-fitimage: Use KERNEL\_OUTPUT\_DIR where appropriate
- kernel-yocto: improve fatal error messages of symbol\_why.py
- kernel: Clear *SYSROOT\_DIRS* instead of replacing sysroot\_stage\_all
- libcap: upgrade 2.65 -> 2.66
- libical: upgrade 3.0.14 -> 3.0.15
- libksba: upgrade 1.6.0 -> 1.6.2
- libSDL2: upgrade 2.24.0 -> 2.24.1
- lighttpd: upgrade 1.4.66 -> 1.4.67
- linux-firmware: package amdgpu firmware
- linux-firmware: split rtl8761 firmware
- linux-yocto/5.15: update to v5.15.72
- linux-yocto/5.19: update to v5.19.14
- linux-yocto: add efi entry for machine features
- lttnng-modules: upgrade 2.13.4 -> 2.13.5
- lttnng-ust: upgrade 2.13.4 -> 2.13.5

- manuals: add reference to "do\_configure" task
- manuals: add reference to the "do\_compile" task
- manuals: add reference to the "do\_install" task
- manuals: add reference to the "do\_kernel\_configcheck" task
- manuals: add reference to the "do\_populate\_sdk" task
- manuals: add references to "do\_package\_write\_\*" tasks
- manuals: add references to "do\_populate\_sysroot" task
- manuals: add references to the "do\_build" task
- manuals: add references to the "do\_bundle\_initramfs" task
- manuals: add references to the "do\_cleanall" task
- manuals: add references to the "do\_deploy" task
- manuals: add references to the "do\_devshell" task
- manuals: add references to the "do\_fetch" task
- manuals: add references to the "do\_image" task
- manuals: add references to the "do\_kernel\_configme" task
- manuals: add references to the "do\_package" task
- manuals: add references to the "do\_package\_qa" task
- manuals: add references to the "do\_patch" task
- manuals: add references to the "do\_rootfs" task
- manuals: add references to the "do\_unpack" task
- manuals: fix misc typos
- manuals: improve initramfs details
- manuals: updates for building on Windows (WSL 2)
- mesa: only apply patch to fix ALWAYS\_INLINE for native
- mesa: update 22.2.0 -> 22.2.2
- meson: make wrapper options sub-command specific
- meson: upgrade 0.63.2 -> 0.63.3
- migration guides: 3.4: remove spurious space in example
- migration guides: add release notes for 4.0.4
- migration-general: add section on using buildhistory
- migration-guides/release-notes-4.1.rst: add more known issues
- migration-guides/release-notes-4.1.rst: update Repositories / Downloads

- migration-guides: add known issues for 4.1
- migration-guides: add reference to the "do\_shared\_workdir" task
- migration-guides: use contributor real name
- migration-guides: use contributor real name
- mirrors.bbclass: use shallow tarball for binutils-native
- mtools: upgrade 4.0.40 -> 4.0.41
- numactl: upgrade 2.0.15 -> 2.0.16
- oe/packagemanager/rpm: don't leak file objects
- openssl: export necessary env vars in SDK
- openssl: Fix SSL\_CERT\_FILE to match ca-certs location
- openssl: Upgrade 3.0.5 -> 3.0.7
- opkg-utils: use a git clone, not a dynamic snapshot
- overlays: Allow not used mount points
- overview-manual: concepts.rst: add reference to "do\_packagedata" task
- overview-manual: concepts.rst: add reference to "do\_populate\_sdk\_ext" task
- overview-manual: concepts.rst: fix formatting and add references
- own-mirrors: add crate
- pango: upgrade 1.50.9 -> 1.50.10
- perf: Depend on native setup tools3
- poky.conf: bump version for 4.1.1
- poky.conf: remove Ubuntu 21.10
- populate\_sdk\_base: ensure ptest-pkgs pulls in ptest-runner
- psplash: add psplash-default in rdepends
- qemu-native: Add *PACKAGECONFIG* option for jack
- quilt: backport a patch to address grep 3.8 failures
- ref-manual/faq.rst: update references to products built with OE / Yocto Project
- ref-manual/variables.rst: clarify sentence
- ref-manual: add a note to ssh-server-dropbear feature
- ref-manual: add *CVE\_CHECK\_SHOW\_WARNINGS*
- ref-manual: add *CVE\_DB\_UPDATE\_INTERVAL*
- ref-manual: add *DEV\_PKG\_DEPENDENCY*
- ref-manual: add *DISABLE\_STATIC*

- ref-manual: add *FIT\_PAD\_ALG*
- ref-manual: add *KERNEL\_DEPLOY\_DEPEND*
- ref-manual: add missing features
- ref-manual: add *MOUNT\_BASE* variable
- ref-manual: add overlayfs class variables
- ref-manual: add *OVERLAYFS\_ETC\_EXPOSE\_LOWER*
- ref-manual: add *OVERLAYFS\_QA\_SKIP*
- ref-manual: add previous overlayfs-etc variables
- ref-manual: add pypi class
- ref-manual: add *SDK\_TOOLCHAIN\_LANGS*
- ref-manual: add section for create-spdx class
- ref-manual: add serial-autologin-root to *IMAGE\_FEATURES* documentation
- ref-manual: add *UBOOT\_MKIMAGE\_KERNEL\_TYPE*
- ref-manual: add *WATCHDOG\_TIMEOUT* to variable glossary
- ref-manual: add *WIRELESS\_DAEMON*
- ref-manual: classes.rst: add links to all references to a class
- ref-manual: complementary package installation recommends
- ref-manual: correct default for *BUILDHISTORY\_COMMIT*
- ref-manual: document new github-releases class
- ref-manual: expand documentation on image-buildinfo class
- ref-manual: faq.rst: reorganize into subsections, contents at top
- ref-manual: remove reference to largefile in *DISTRO\_FEATURES*
- ref-manual: remove reference to testimage-auto class
- ref-manual: system-requirements: Ubuntu 22.04 now supported
- ref-manual: tasks.rst: add reference to the "do\_image\_complete" task
- ref-manual: tasks.rst: add reference to the "do\_kernel\_checkout" task
- ref-manual: tasks.rst: add reference to the "do\_kernel\_metadata" task
- ref-manual: tasks.rst: add reference to the "do\_validate\_branches" task
- ref-manual: tasks.rst: add references to the "do\_cleansstate" task
- ref-manual: update buildpaths QA check documentation
- ref-manual: update pypi documentation for *CVE\_PRODUCT* default in 4.1
- ref-manual: variables.rst: add reference to "do\_populate\_lic" task

- release-notes-4.1.rst remove bitbake-layers subcommand argument
- runqemu: Do not perturb script environment
- runqemu: Fix gl-es argument from causing other arguments to be ignored
- rust-target-config: match riscv target names with what rust expects
- rust: install rustfmt for riscv32 as well
- sanity: check for GNU tar specifically
- scripts/oe-check-sstate: cleanup
- scripts/oe-check-sstate: force build to run for all targets, specifically populate\_sysroot
- sdk-manual: correct the bitbake target for a unified sysroot build
- shadow: update 4.12.1 -> 4.12.3
- systemd: add systemd-creds and systemd-cryptenroll to systemd-extra-utils
- test-manual: fix typo in machine name
- tiff: fix a typo for [CVE-2022-2953](#).patch
- u-boot: Add savedefconfig task
- u-boot: Remove duplicate inherit of cml1
- uboot-sign: Fix using wrong KEY\_REQ\_ARGS
- Update documentation for classes split
- vim: upgrade to 9.0.0820
- vulkan-samples: add lfs=0 to [SRC\\_URI](#) to avoid git smudge errors in do\_unpack
- wic: honor the [SOURCE\\_DATE\\_EPOCH](#) in case of updated fstab
- wic: swap partitions are not added to fstab
- wpebackend-fdo: upgrade 1.12.1 -> 1.14.0
- xserver-xorg: move some recommended dependencies in required
- zlib: do out-of-tree builds
- zlib: upgrade 1.2.12 -> 1.2.13
- zlib: use .gz archive and set a PREMIRROR

#### Known Issues in Yocto-4.1.1

- N/A

### Contributors to Yocto-4.1.1

- Adrian Freihofer
- Alex Kiernan
- Alexander Kanavin
- Bartosz Golaszewski
- Bernhard Rosenkränzer
- Bruce Ashfield
- Chen Qi
- Christian Eggers
- Claus Stovgaard
- Ed Tanous
- Etienne Cordonnier
- Frank de Brabander
- Hitendra Prajapati
- Jan-Simon Moeller
- Jeremy Puhlman
- Johan Korsnes
- Jon Mason
- Jose Quaresma
- Joshua Watt
- Justin Bronder
- Kai Kang
- Keiya Nobuta
- Khem Raj
- Lee Chee Yang
- Liam Beguin
- Luca Boccassi
- Mark Asselstine
- Mark Hatle
- Markus Volk
- Martin Jansa
- Michael Opdenacker

- Ming Liu
- Mingli Yu
- Paul Eggleton
- Peter Kjellerstedt
- Qiu, Zheng
- Quentin Schulz
- Richard Purdie
- Robert Joslyn
- Ross Burton
- Sean Anderson
- Sergei Zhmylev
- Steve Sakoman
- Takayasu Ito
- Teoh Jay Shen
- Thomas Perrot
- Tim Orling
- Vincent Davis Jr
- Vyacheslav Yurkov
- Ciaran Courtney
- Wang Mingyu

## Repositories / Downloads for Yocto-4.1.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [langdale](#)
- Tag: [yocto-4.1.1](#)
- Git Revision: [d3cda9a3e0837eb2ac5482f5f2bd8e55e874feff](#)
- Release Artefact: [poky-d3cda9a3e0837eb2ac5482f5f2bd8e55e874feff](#)
- sha: [e92b694fbb74a26c7a875936dfeef4a13902f24b06127ee52f4d1c1e4b03ec24](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.1/poky-d3cda9a3e0837eb2ac5482f5f2bd8e55e874feff.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.1/poky-d3cda9a3e0837eb2ac5482f5f2bd8e55e874feff.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>

- Branch: `langdale`
- Tag: `yocto-4.1.1`
- Git Revision: `9237ffc4feee2dd6ff5bdd672072509ef9e82f6d`
- Release Artefact: `oecore-9237ffc4feee2dd6ff5bdd672072509ef9e82f6d`
- sha: `d73198aef576f0fca0d746f9d805b1762c19c31786bc3f7d7326dfb2ed6fc1be`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.1/oecore-9237ffc4feee2dd6ff5bdd672072509ef9e82f6d.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.1/oecore-9237ffc4feee2dd6ff5bdd672072509ef9e82f6d.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `langdale`
- Tag: `yocto-4.1.1`
- Git Revision: `b0067202db8573df3d23d199f82987cebe1bee2c`
- Release Artefact: `meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c`
- sha: `704f2940322b81ce774e9cbd27c3fa843111d497dc7b1eaa39cd694d9a2366`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.1/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.1/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.2`
- Tag: `yocto-4.1.1`
- Git Revision: `138dd7883ee2c521900b29985b6d24a23d96563c`
- Release Artefact: `bitbake-138dd7883ee2c521900b29985b6d24a23d96563c`
- sha: `5dc5aff4b4a801253c627cdaab6b1a0ceee2c531f1a6b166d85d1265a35d4be5`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.1/bitbake-138dd7883ee2c521900b29985b6d24a23d96563c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.1/bitbake-138dd7883ee2c521900b29985b6d24a23d96563c.tar.bz2>

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `langdale`
- Tag: `yocto-4.1.1`
- Git Revision: `8e0841c3418caa227c66a60327db09dfbe72054a`



## 17.10.4 Release notes for Yocto-4.1.2 (Langdale)

### Security Fixes in Yocto-4.1.2

- sudo: Fix [CVE-2022-43995](#)
- binutils: Fix [CVE-2022-4285](#)
- cairo: update patch for [CVE-2019-6461](#) with upstream solution
- expat: Fix [CVE-2022-43680](#)
- ffmpeg: Fix [CVE-2022-3964](#) and [CVE-2022-3965](#)
- grub: Fix [CVE-2022-28736](#)
- libarchive: Fix [CVE-2022-36227](#)
- libpam: Fix [CVE-2022-28321](#)
- libpng: Fix [CVE-2019-6129](#)
- ruby: Fix [CVE-2022-28738](#) and [CVE-2022-28739](#)
- tiff: Fix [CVE-2022-3970](#)
- vim: Fix [CVE-2022-4141](#)

### Fixes in Yocto-4.1.2

- Expand create-spdx class documentation
- Expand cve-check class documentation
- archiver: avoid using machine variable as it breaks multiconfig
- babeltrace: Upgrade to 1.5.11
- backport SPDX documentation and vulnerability improvements
- baremetal-image: Avoid overriding qemu variables from IMAGE\_CLASSES
- bc: extend to nativesdk
- bind: Upgrade to 9.18.9
- bitbake.conf: Drop export of SOURCE\_DATE\_EPOCH\_FALLBACK
- bitbake: git-sm: Fix regression in git-sm submodule path parsing
- bitbake: runqueue: Fix race issues around hash equivalence and sstate reuse
- bluez5: Point hciattach bcm43xx firmware search path to /lib/firmware
- build-appliance-image: Update to langdale head revision
- cargo\_common.bbclass: Fix typos
- classes: make TOOLCHAIN more permissive for kernel
- cmake: Upgrade to 3.24.2
- combo-layer: add sync-revs command

- combo-layer: dont use bb.utils.rename
- combo-layer: remove unused import
- common-tasks.rst: fix oeqa runtime test path
- create-spdx: default share\_src for shared sources
- curl: Correct LICENSE from MIT-open-group to curl
- dbus: Add missing CVE product name
- devtool/upgrade: correctly handle recipes where S is a subdir of upstream tree
- dhcpcd: fix to work with systemd
- docs: kernel-dev: faq: update tip on how to not include kernel in image
- docs: migration-4.0: specify variable name change for kernel inclusion in image recipe
- expat: upgrade to 2.5.0
- externalsrc: fix lookup for .gitmodules
- ffmpeg: Upgrade to 5.1.2
- gcc-shared-source: Fix source date epoch handling
- gcc-source: Drop gengtype manipulation
- gcc-source: Ensure deploy\_source\_date\_epoch sstate hash doesn't change
- gcc-source: Fix gengtypes race
- gdk-pixbuf: Upgrade to 2.42.10
- get\_module\_deps3.py: Check attribute '\_\_file\_\_'
- glibc-tests: correctly pull in the actual tests when installing -ptest package
- gnomebase.bbclass: return the whole version for tarball directory if it is a number
- go-crosssdk: avoid host contamination by GOCACHE
- go: Update reproducibility patch to fix panic errors
- go: submit patch upstream
- go: Upgrade to 1.19.3
- gptfdisk: remove warning message from target system
- groff: submit patches upstream
- gstreamer1.0: Upgrade to 1.20.5
- help2man: Upgrade to 1.49.3
- insane: add codeload.github.com to src-uri-bad checkz
- inetutils: Upgrade to 2.4
- iso-codes: Upgrade to 4.12.0

- kbd: Don't build tests
- kea: submit patch upstream
- kern-tools: integrate ZFS speedup patch
- kernel.bbclass: Include randstruct seed assets in STAGING\_KERNEL\_BUILDDIR
- kernel.bbclass: make KERNEL\_DEBUG\_TIMESTAMPS work at rebuild
- kernel.bbclass: remove empty module directories to prevent QA issues
- lib/buildstats: fix parsing of trees with reduced\_proc\_pressure directories
- libdrm: Remove libdrm-kms package
- libepoxy: convert to git
- libepoxy: remove upstreamed patch
- libepoxy: Upgrade to 1.5.10
- libffi: submit patch upstream
- libffi: Upgrade to 3.4.4
- libical: Upgrade to 3.0.16
- libnewt: Upgrade to 0.52.23
- libSDL2: Upgrade to 2.24.2
- libpng: Upgrade to 1.6.39
- libuv: fixup SRC\_URI
- libxcrypt-compat: Upgrade to 4.4.33
- libxcrypt: Upgrade to 4.4.30
- libxml2: fix test data checksums
- linux-firmware: add new fw file to \${PN}-qcom-adreno-a530
- linux-firmware: don't put the firmware into the sysroot
- linux-firmware: Upgrade to 20221109
- linux-yocto/5.15: fix CONFIG\_CRYPTOC\_CCM mismatch warnings
- linux-yocto/5.15: update genericx86\* machines to v5.15.72
- linux-yocto/5.15: Upgrade to v5.15.78
- linux-yocto/5.19: cfg: intel and vesa updates
- linux-yocto/5.19: fix CONFIG\_CRYPTOC\_CCM mismatch warnings
- linux-yocto/5.19: fix elfutils run-backtrace-native-core ptest failure
- linux-yocto/5.19: security.cfg: remove configs which have been dropped
- linux-yocto/5.19: update genericx86\* machines to v5.19.14

- linux-yocto/5.19: Upgrade to v5.19.17
- lsof: add update-alternatives logic
- lttnng-modules: Upgrade to 2.13.7
- lttnng-tools: submit determinism.patch upstream
- manuals: add 4.0.5 and 4.0.6 release notes
- mesa: do not rely on native llvm-config in target sysroot
- mesa: Upgrade to 22.2.3
- meta-selftest/staticids: add render group for systemd
- mirrors.bbclass: update CPAN\_MIRROR
- mobile-broadband-provider-info: Upgrade to 20221107
- mpfr: Upgrade to 4.1.1
- mtd-utils: Upgrade to 2.1.5
- oeqa/concurrencytest: Add number of failures to summary output
- oeqa/runtime/dnf: rewrite test\_dnf\_installroot\_usrmerge
- oeqa/selftest/externalsrc: add test for srcree\_hash\_files
- oeqa/selftest/lic\_checksum: Cleanup changes to emptytest include
- openssh: remove RRECOMMENDS to rng-tools for sshd package
- opkg: Set correct info\_dir and status\_file in opkg.conf
- opkg: Upgrade to 0.6.1
- ovmf: correct patches status
- package: Fix handling of minidebuginfo with newer binutils
- pango: Make it build with ptest disabled
- pango: replace a recipe fix with an upstream submitted patch
- pango: Upgrade to 1.50.11
- poky.conf: bump version for 4.1.2
- psplash: consider the situation of psplash not exist for systemd
- python3-mako: Upgrade to 1.2.3
- qemu-helper-native: Correctly pass program name as argv[0]
- qemu-helper-native: Re-write bridge helper as C program
- qemu: Ensure libpng dependency is deterministic
- qemuboot.bbclass: make sure runqemu boots bundled initramfs kernel image
- resolvconf: make it work

- `rm_work`: adjust dependency to make `do_rm_work_all` depend on `do_rm_work`
- `rm_work`: exclude the `SSTATETASKS` from the `rm_work` tasks signature
- `ruby`: merge `.inc` into `.bb`
- `ruby`: Upgrade to 3.1.3
- `rust`: submit a rewritten version of `crossbeam_atomic.patch` upstream
- `sanity`: Drop data finalize call
- `scripts`: convert-overrides: Allow command-line customizations
- `selftest`: add a copy of previous `mtt-utils` version to `meta-selftest`
- `socat`: Upgrade to 1.7.4.4
- `sstate`: Allow optimisation of `do_deploy_archives` task dependencies
- `sstatesig`: emit more helpful error message when not finding `sstate` manifest
- `sstatesig`: skip the `rm_work` task signature
- `sudo`: Upgrade to 1.9.12p1
- `sysstat`: Upgrade to 12.6.1
- `systemd`: Consider `PACKAGECONFIG` in `RRECOMMENDS`
- `systemd`: Make `importd` depend on `glib-2.0` again
- `systemd`: add group `render` to `udev` package
- `systemd`: Upgrade to 251.8
- `tcl`: correct patch status
- `tzdata`: Upgrade to 2022g
- `vala`: install `vapigen-wrapper` into `/usr/bin/crosscripts` and stage only that
- `valgrind`: skip the `boost_thread` test on arm
- `vim`: Upgrade to 9.0.0947
- `wic`: make `ext2/3/4` images reproducible
- `xwayland`: `libxshmfence` is needed when `dri3` is enabled
- `xwayland`: Upgrade to 22.1.5
- `yocto-check-layer`: Allow OE-Core to be tested

### Known Issues in Yocto-4.1.2

- N/A

## Contributors to Yocto-4.1.2

- Alejandro Hernandez Samaniego
- Alex Kiernan
- Alex Stewart
- Alexander Kanavin
- Alexey Smirnov
- Bruce Ashfield
- Carlos Alberto Lopez Perez
- Chen Qi
- Diego Sueiro
- Dmitry Baryshkov
- Enrico Jörns
- Harald Seiler
- Hitendra Prajapati
- Jagadeesh Krishnanjanappa
- Jose Quaresma
- Joshua Watt
- Kai Kang
- Konrad Weihmann
- Leon Anavi
- Marek Vasut
- Martin Jansa
- Mathieu Dubois-Briand
- Michael Opdenacker
- Mikko Rapeli
- Narpat Mali
- Nathan Rossi
- Niko Mauno
- Ola x Nilsson
- Ovidiu Panait
- Pavel Zhukov
- Peter Bergin

- Peter Kjellerstedt
- Peter Marko
- Polampalli, Archana
- Qiu, Zheng
- Quentin Schulz
- Randy MacLeod
- Ranjitsinh Rathod
- Ravula Adhitya Siddartha
- Richard Purdie
- Robert Andersson
- Ross Burton
- Ryan Eatmon
- Sakib Sajal
- Sandeep Gundlupet Raju
- Sergei Zhmylev
- Steve Sakoman
- Tim Orling
- Wang Mingyu
- Xiangyu Chen
- pgowda

## Repositories / Downloads for Yocto-4.1.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [langdale](#)
- Tag: [yocto-4.1.2](#)
- Git Revision: [74c92e38c701e268406bb656b45ccd68471c217e](#)
- Release Artefact: [poky-74c92e38c701e268406bb656b45ccd68471c217e](#)
- sha: [06a2b304d0e928b62d81087797ae86115efe925c506bcb40c7d4747e14790bb0](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.2/poky-74c92e38c701e268406bb656b45ccd68471c217e.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.2/poky-74c92e38c701e268406bb656b45ccd68471c217e.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>

- Branch: langdale
- Tag: yocto-4.1.2
- Git Revision: 670f4f103b25897524d115c1f290ecae441fe4bd
- Release Artefact: oecore-670f4f103b25897524d115c1f290ecae441fe4bd
- sha: 09d77700e84efc738aef5713c5e86f19fa092f876d44b870789155cc1625ef04
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.2/oecore-670f4f103b25897524d115c1f290ecae441fe4bd.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.2/oecore-670f4f103b25897524d115c1f290ecae441fe4bd.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: langdale
- Tag: yocto-4.1.2
- Git Revision: b0067202db8573df3d23d199f82987cebe1bee2c
- Release Artefact: meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c
- sha: 704f2940322b81ce774e9cbd27c3cfa843111d497dc7b1eaa39cd694d9a2366
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.2/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.2/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.2
- Tag: yocto-4.1.2
- Git Revision: f0f166aee766b4bb1f8cf8b35dfc7d406c75e6a4
- Release Artefact: bitbake-f0f166aee766b4bb1f8cf8b35dfc7d406c75e6a4
- sha: 7faf97eca78afd3994e4e126e5f5908617408c340c6eff8cd7047e0b961e2d10
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.2/bitbake-f0f166aee766b4bb1f8cf8b35dfc7d406c75e6a4.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.2/bitbake-f0f166aee766b4bb1f8cf8b35dfc7d406c75e6a4.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: langdale
- Tag: yocto-4.1.2
- Git Revision: 30f5f9ece260fd600f0c0fa32fc2f1fc61cf7d1b



## 17.10.5 Release notes for Yocto-4.1.3 (Langdale)

### Security Fixes in Yocto-4.1.3

- apr-util: Fix CVE-2022-25147
- apr: Fix CVE-2022-24963 and CVE-2022-28331
- bind: Fix CVE-2022-3094, CVE-2022-3736 and CVE-2022-3924
- curl: Fix CVE-2022-43551 and CVE-2022-43552
- dbus: Fix CVE-2022-42010, CVE-2022-42011 and CVE-2022-42012
- git: Fix CVE-2022-23521, CVE-2022-39253, CVE-2022-39260 and CVE-2022-41903
- git: Ignore CVE-2022-41953
- go: Fix CVE-2022-41717 and CVE-2022-41720
- grub2: Fix CVE-2022-2601 and CVE-2022-3775
- less: Fix CVE-2022-46663
- libarchive: Fix CVE-2022-36227
- libksba: Fix CVE-2022-47629
- openssl: Fix CVE-2022-3996
- pkgconf: Fix CVE-2023-24056
- ppp: Fix CVE-2022-4603
- sudo: Fix CVE-2023-22809
- tar: Fix CVE-2022-48303
- vim: Fix CVE-2023-0049, CVE-2023-0051, CVE-2023-0054, CVE-2023-0288, CVE-2023-0433 and CVE-2023-0512
- xserver-xorg: Fix CVE-2023-0494
- xwayland: Fix CVE-2023-0494

### Fixes in Yocto-4.1.3

- apr-util: Upgrade to 1.6.3
- apr: Upgrade to 1.7.2
- apt: fix do\_package\_qa failure
- at: Change when files are copied
- base.bbclass: Fix way to check ccache path
- bblayers/makesetup: skip git repos that are submodules
- bblayers/setupwriters/oe-setup-layers: create dir if not exists
- bind: Upgrade to 9.18.11

- bitbake-layers: fix a typo
- bitbake: bb/utils: include SSL certificate paths in export\_proxies
- bitbake: fetch2/git: Clarify the meaning of namespace
- bitbake: fetch2/git: Prevent git fetcher from fetching gitlab repository metadata
- bitbake: process: log odd unlink events with bitbake.sock
- bitbake: server/process: Add bitbake.sock race handling
- bitbake: siggen: Fix inefficient string concatenation
- bootchart2: Fix usrmerge support
- bsp-guide: fix broken git URLs and missing word
- build-appliance-image: Update to langdale head revision
- buildtools-tarball: set pkg-config search path
- busybox: Fix depmod patch
- busybox: always start do\_compile with orig config files
- busybox: rm temporary files if do\_compile was interrupted
- cairo: fix CVE patches assigned wrong CVE number
- classes/fs-uuid: Fix command output decoding issue
- classes/populate\_sdk\_base: Append cleandirs
- classes: image: Set empty weak default IMAGE\_LINGUAS
- cml1: remove redundant addtask
- core-image.bbclass: Fix missing leading whitespace with 'append'
- createrepo-c: Include missing rpm/rpmstring.h
- curl: don't enable debug builds
- curl: fix dependencies when building with ldap/ldaps
- cve-check: write the cve manifest to IMGDEPLOYDIR
- cve-update-db-native: avoid incomplete updates
- cve-update-db-native: show IP on failure
- dbus: Upgrade to 1.14.6
- dev-manual: common-tasks.rst: add link to FOSDEM 2023 video
- dev-manual: fix old override syntax
- devshell: Do not add scripts/git-intercept to PATH
- devtool: fix devtool finish when gitmodules file is empty
- devtool: process local files only for the main branch

- dhcpcd: backport two patches to fix runtime error
- dhcpcd: fix dhcpcd start failure on qemuppc64
- diffutils: Upgrade to 3.9
- ffmpeg: fix configure failure on noexec /tmp host
- gdk-pixbuf: do not use tools from gdk-pixbuf-native when building tests
- git: Upgrade to 2.37.6
- glslang: branch rename master -> main
- go: Upgrade to 1.19.4
- gstreamer1.0 : Revert "disable flaky gstbin:test\_watch\_for\_state\_change test" and Fix race conditions in gstbin tests with upstream solution
- harfbuzz: remove bindir only if it exists
- httpserver: add error handler that write to the logger
- image.bbclass: print all QA functions exceptions
- kernel-fitimage: Adjust order of dtb/dtbo files
- kernel-fitimage: Allow user to select dtb when multiple dtb exists
- kernel-yocto: fix kernel-meta data detection
- kernel/linux-kernel-base: Fix kernel build artefact determinism issues
- lib/buildstats: handle tasks that never finished
- lib/oe/reproducible: Use git log without gpg signature
- libarchive: Upgrade to 3.6.2
- libc-locale: Fix on target locale generation
- libgit2: Upgrade to 1.5.1
- libjpeg-turbo: Upgrade to 2.1.5.1
- libksba: Upgrade to 1.6.3
- libpng: Enable NEON for aarch64 to ensure consistency with arm32.
- libsvg: Only enable the Vala bindings if GObject Introspection is enabled
- libsvg: enable vapi build
- libseccomp: fix for the ptest result format
- libseccomp: fix typo in DESCRIPTION
- libssh2: Clean up ptest patch/coverage
- libtirpc: Check if file exists before operating on it
- libusb1: Link with libatomic only if compiler has no atomic builtins
- libusb1: Strip trailing whitespaces

- linux-firmware: add yamato fw files to qcom-adreno-a2xx package
- linux-firmware: properly set license for all Qualcomm firmware
- linux-firmware: Upgrade to 20230210
- linux-yocto/5.15: fix perf build with clang
- linux-yocto/5.15: libbpf: Fix build warning on ref\_ctr\_off
- linux-yocto/5.15: ltp and squashfs fixes
- linux-yocto/5.15: powerpc: Fix reschedule bug in KUAP-unlocked user copy
- linux-yocto/5.15: Upgrade to v5.15.91
- linux-yocto/5.19: fix perf build with clang
- linux-yocto/5.19: powerpc: Fix reschedule bug in KUAP-unlocked user copy
- lsof: fix old override syntax
- lttnng-modules: Fix for 5.10.163 kernel version
- lttnng-modules: fix for kernel 6.2+
- lttnng-modules: Upgrade to 2.13.8
- lttnng-tools: Upgrade to 2.13.9
- make-mod-scripts: Ensure kernel build output is deterministic
- manuals: update patchwork instance URL
- mesa-gl: gallium is required when enabling x11
- meta: remove True option to getVar and getVarFlag calls (again)
- migration-guides: add release-notes for 4.0.7
- native: Drop special variable handling
- numactl: skip test case when target platform doesn't have 2 CPU node
- oeqa context.py: fix --target-ip comment to include ssh port number
- oeqa dump.py: add error counter and stop after 5 failures
- oeqa qemurunner.py: add timeout to QMP calls
- oeqa qemurunner.py: try to avoid reading one character at a time
- oeqa qemurunner: read more data at a time from serial
- oeqa ssh.py: add connection keep alive options to ssh client
- oeqa ssh.py: fix hangs in run()
- oeqa ssh.py: move output prints to new line
- oeqa/qemurunner: do not use Popen.poll() when terminating runqemu with a signal
- oeqa/rpm.py: Increase timeout and add debug output

- oeqa/selftest/debuginfod: improve testcase
- oeqa/selftest/locales: Add selftest for locale generation/presence
- oeqa/selftest/resulttooltests: fix minor typo
- openssl: Upgrade to 3.0.8
- opkg: ensure opkg uses private gpg.conf when applying keys.
- pango: Upgrade to 1.50.12
- perf: Enable debug/source packaging
- pkgconf: Upgrade to 1.9.4
- poky.conf: Update SANITY\_TESTED\_DISTROS to match autobuilder
- poky.conf: bump version for 4.1.3
- populate\_sdk\_ext.bbclass: Fix missing leading whitespace with ':append'
- profile-manual: update WireShark hyperlinks
- ptest-packagelists.inc: Fix missing leading whitespace with ':append'
- python3-pytest: depend on python3-tomli instead of python3-toml
- quilt: fix intermittent failure in faildiff.test
- quilt: use upstreamed faildiff.test fix
- recipe\_sanity: fix old override syntax
- ref-manual: Fix invalid feature name
- ref-manual: update DEV\_PKG\_DEPENDENCY in variables
- ref-manual: variables.rst: fix broken hyperlink
- rm\_work.bbclass: use HOSTTOOLS 'rm' binary exclusively
- runqemu: kill qemu if it hangs
- rust: Do not use default compiler flags defined in CC crate
- scons.bbclass: Make MAXLINELENGTH overridable
- scons: Pass MAXLINELENGTH to scons invocation
- sdkext/cases/devtool: pass a logger to HTTPService
- selftest/virgl: use pkg-config from the host
- spirv-headers/spirv-tools: set correct branch name
- sstate.bbclass: Fetch non-existing local .sig files if needed
- sstatesig: Improve output hash calculation
- sudo: Upgrade to 1.9.12p2
- system-requirements.rst: Add Fedora 36, AlmaLinux 8.7 & 9.1, and OpenSUSE 15.4 to list of supported distros

- testimage: Fix error message to reflect new syntax
- tiff: Add packageconfig knob for webp
- toolchain-scripts: compatibility with unbound variable protection
- uninative: Upgrade to 3.8.1 to include libgcc
- update-alternatives: fix typos
- vim: Upgrade to 9.0.1293
- vulkan-samples: branch rename master -> main
- wic: Fix usage of fstype=none in wic
- wireless-regdb: Upgrade to 2023.02.13
- xserver-xorg: Upgrade to 21.1.7
- xwayland: Upgrade to 22.1.8

### **Known Issues in Yocto-4.1.3**

- N/A

### **Contributors to Yocto-4.1.3**

- Adrian Freihofer
- Alejandro Hernandez Samaniego
- Alex Kiernan
- Alexander Kanavin
- Alexis Lothoré
- Anton Antonov
- Antonin Godard
- Armin Kuster
- Arnout Vandecappelle
- Benoît Mauduit
- Bruce Ashfield
- Carlos Alberto Lopez Perez
- Changqing Li
- Charlie Johnston
- Chee Yang Lee
- Chen Qi
- Dmitry Baryshkov
- Enguerrand de Ribaucourt

- Etienne Cordonnier
- Fawzi KHABER
- Federico Pellegrin
- Frank de Brabander
- Harald Seiler
- He Zhe
- Jan Kircher
- Jermain Horsman
- Jose Quaresma
- Joshua Watt
- Kai Kang
- Khem Raj
- Lei Maohui
- Louis Rannou
- Luis
- Marek Vasut
- Markus Volk
- Marta Rybczynska
- Martin Jansa
- Mateusz Marciniec
- Mauro Queiros
- Michael Halstead
- Michael Opdenacker
- Mikko Rapeli
- Mingli Yu
- Narpat Mali
- Niko Mauno
- Pavel Zhukov
- Pawel Zalewski
- Peter Kjellerstedt
- Petr Kubizňák
- Quentin Schulz

- Randy MacLeod
- Richard Purdie
- Robert Joslyn
- Rodolfo Quesada Zumbado
- Ross Burton
- Sakib Sajal
- Sandeep Gundlupet Raju
- Saul Wold
- Siddharth Doshi
- Steve Sakoman
- Thomas Roos
- Tobias Hagelborn
- Ulrich Ölmann
- Vivek Kumbhar
- Wang Mingyu
- Xiangyu Chen

### Repositories / Downloads for Yocto-4.1.3

#### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [langdale](#)
- Tag: [yocto-4.1.3](#)
- Git Revision: [91d0157d6daf4ea61d6b4e090c0b682d3f3ca60f](#)
- Release Artefact: [poky-91d0157d6daf4ea61d6b4e090c0b682d3f3ca60f](#)
- sha: [94e4615eba651fe705436b29b854458be050cc39db936295f9d5eb7e85d3eff1](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.3/poky-91d0157d6daf4ea61d6b4e090c0b682d3f3ca60f.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.3/poky-91d0157d6daf4ea61d6b4e090c0b682d3f3ca60f.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [langdale](#)
- Tag: [yocto-4.1.3](#)
- Git Revision: [b995ea45773211bd7bdd60eabcc9bbffda6beb5c](#)
- Release Artefact: [oecore-b995ea45773211bd7bdd60eabcc9bbffda6beb5c](#)



- sha: 952e19361f205ee91b74e5caaa835d58fa6dd0d92ddaed50d4cd3f3fa56fab63
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.3/oecore-b995ea45773211bd7bdd60eabcc9bbffda6beb5c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.3/oecore-b995ea45773211bd7bdd60eabcc9bbffda6beb5c.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: langdale
- Tag: yocto-4.1.3
- Git Revision: b0067202db8573df3d23d199f82987cebe1bee2c
- Release Artefact: meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c
- sha: 704f2940322b81ce774e9cbd27c3fa843111d497dc7b1eaa39cd694d9a2366
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.3/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.3/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.2
- Tag: yocto-4.1.3
- Git Revision: 592ee222a1c6da42925fb56801f226884b6724ec
- Release Artefact: bitbake-592ee222a1c6da42925fb56801f226884b6724ec
- sha: 79c32f2ca66596132e32a45654ce0e9dd42b6b39186eff3540a9d6b499fe952c
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.3/bitbake-592ee222a1c6da42925fb56801f226884b6724ec.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.3/bitbake-592ee222a1c6da42925fb56801f226884b6724ec.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: langdale
- Tag: yocto-4.1.3
- Git Revision: 3de2ad1f8ff87aeec30088779267880306a0f31a

## 17.10.6 Release notes for Yocto-4.1.4 (Langdale)

### Security Fixes in Yocto-4.1.4

- cve-extra-exclusions/linux-yocto: Ignore CVE-2020-27784, CVE-2021-3669, CVE-2021-3759, CVE-2021-4218, CVE-2022-0480, CVE-2022-1184, CVE-2022-1462, CVE-2022-2308, CVE-2022-2327, CVE-2022-26365, CVE-2022-2663, CVE-2022-2785, CVE-2022-3176, CVE-2022-33740, CVE-2022-33741,

CVE-2022-33742, CVE-2022-3526, CVE-2022-3563, CVE-2022-3621, CVE-2022-3623, CVE-2022-3624, CVE-2022-3625, CVE-2022-3629, CVE-2022-3630, CVE-2022-3633, CVE-2022-3635, CVE-2022-3636, CVE-2022-3637, CVE-2022-3646 and CVE-2022-3649

- cve-extra-exclusions/linux-yocto 5.15: Ignore CVE-2022-3435, CVE-2022-3534, CVE-2022-3564, CVE-2022-3564, CVE-2022-3619, CVE-2022-3640, CVE-2022-42895, CVE-2022-42896, CVE-2022-4382, CVE-2023-0266 and CVE-2023-0394
- epiphany: Fix CVE-2023-26081
- git: Ignore CVE-2023-22743
- go: Fix CVE-2022-41722, CVE-2022-41723, CVE-2022-41724, CVE-2022-41725 and CVE-2023-24532
- harfbuzz: Fix CVE-2023-25193
- libmicrohttpd: Fix CVE-2023-27371
- libxml2: Fix CVE-2022-40303 and CVE-2022-40304
- openssl: Fix CVE-2023-0464, CVE-2023-0465 and CVE-2023-0466
- python3-setuptools: Fix CVE-2022-40897
- qemu: Fix CVE-2022-4144
- screen: Fix CVE-2023-24626
- shadow: Ignore CVE-2016-15024
- tiff: Fix CVE-2022-48281, CVE-2023-0795, CVE-2023-0796, CVE-2023-0797, CVE-2023-0798, CVE-2023-0799, CVE-2023-0800, CVE-2023-0801, CVE-2023-0802, CVE-2023-0803 and CVE-2023-0804
- vim: Fix CVE-2023-1127, CVE-2023-1170, CVE-2023-1175, CVE-2023-1264 and CVE-2023-1355
- xdg-utils: Fix CVE-2022-4055
- xserver-xorg: Fix for CVE-2023-1393

#### **Fixes in Yocto-4.1.4**

- apt: re-enable version check
- base-files: Drop localhost.localdomain from hosts file
- binutils: Fix nativesdk ld.so search
- bitbake: bin/utis: Ensure locale en\_US.UTF-8 is available on the system
- bitbake: cookerdata: Drop dubious exception handling code
- bitbake: cookerdata: Improve early exception handling
- bitbake: cookerdata: Remove incorrect SystemExit usage
- bitbake: fetch/git: Fix local clone url to make it work with repo
- bitbake: toaster: Add refreshed oe-core and poky fixtures
- bitbake: toaster: fixtures/README: django 1.8 -> 3.2

- bitbake: toaster: fixtures/gen\_fixtures.py: update branches
- bitbake: utils: Allow to\_boolean to support int values
- bmap-tools: switch to main branch
- build-appliance-image: Update to langdale head revision
- buildtools-tarball: Handle spaces within user \$PATH
- busybox: move hwclock init earlier in startup
- cargo.bbclass: use offline mode for building
- cpio: Fix wrong CRC with ASCII CRC for large files
- cracklib: update github branch to 'main'
- cups: add/fix web interface packaging
- cups: check *PACKAGECONFIG* for pam feature
- cups: use BUILDROOT instead of DESTDIR
- cve-check: Fix false negative version issue
- devtool/upgrade: do not delete the workspace/recipes directory
- dhcpd: Fix install conflict when enable multilib.
- ffmpeg: fix build failure when vulkan is enabled
- filemap.py: enforce maximum of 4kb block size
- gcc-shared-source: do not use \${S}/.. in deploy\_source\_date\_epoch
- glibc: Add missing binutils dependency
- go: upgrade to 1.19.7
- image\_types: fix multiubi var init
- image\_types: fix vname var init in multiubi\_mkfs() function
- iso-codes: upgrade to 4.13.0
- kernel-devsrc: fix mismatched compiler warning
- lib/oe/gpg\_sign.py: Avoid race when creating .sig files in detach\_sign
- lib/resulttool: fix typo breaking resulttool log --ptest
- libcomps: Fix callback function prototype for PyCOMPS\_hash
- libdnf: upgrade to 0.70.0
- libgit2: update license information
- libmicrohttpd: upgrade to 0.9.76
- linux-yocto-rt/5.15: upgrade to -rt59
- linux-yocto/5.15: upgrade to v5.15.108

- linux: inherit pkgconfig in kernel.bbclass
- lttnng-modules: upgrade to v2.13.9
- lua: Fix install conflict when enable multilib.
- mdadm: Fix raid0, 06wrmstly and 02lineargrow tests
- mesa-demos: packageconfig weston should have a dependency on wayland-protocols
- meson: Fix wrapper handling of implicit setup command
- meson: remove obsolete RPATH stripping patch
- migration-guides: update release notes
- oeqa ping.py: avoid busylooping failing ping command
- oeqa ping.py: fail test if target IP address has not been set
- oeqa rtc.py: skip if read-only-rootfs
- oeqa/runtime: clean up deprecated backslash expansion
- oeqa/sdk: Improve Meson test
- oeqa/selftest/cases/package.py: adding unittest for package rename conflicts
- oeqa/selftest/cases/runqemu: update imports
- oeqa/selftest/prservice: Improve debug output for failure
- oeqa/selftest/reproducible: Split different packages from missing packages output
- oeqa/selftest: OESelftestTestContext: convert relative to full path when newbuilddir is provided
- oeqa/targetcontrol: do not set dump\_host\_cmds redundantly
- oeqa/targetcontrol: fix misspelled RuntimeError
- oeqa/targetcontrol: remove unused imports
- oeqa/utls/commands: fix usage of undefined EPIPE
- oeqa/utls/commands: remove unused imports
- oeqa/utls/qemurunner: replace hard-coded user 'root' in debug output
- oeqs/selftest: OESelftestTestContext: replace the os.environ after subprocess.check\_output
- package.bbclass: check packages name conflict in do\_package
- pango: upgrade to 1.50.13
- piglit: Fix build time dependency
- poky.conf: bump version for 4.1.4
- populate\_sdk\_base: add zip options
- populate\_sdk\_ext: Handle spaces within user \$PATH
- pybootchart: Fix extents handling to account for cpu/io/mem pressure changes

- pybootchartui: Fix python syntax issue
- report-error: catch Nothing *PROVIDES* error
- rpm: Fix hdr\_hash function prototype
- run-postinsts: Set dependency for ldconfig to avoid boot issues
- runqemu: respect *IMAGE\_LINK\_NAME*
- runqemu: Revert "workaround for APIC hang on pre 4.15 kernels on qemu86q"
- scripts/lib/buildstats: handle top-level build\_stats not being complete
- selftest/recipe tool: Stop test corrupting tinfoil class
- selftest/runtime\_test/virgl: Disable for all Rocky Linux
- selftest: devtool: set *BB\_HASHSERVE\_UPSTREAM* when setting *SSTATE\_MIRRORS*
- selftest: runqemu: better check for ROOTFS: in the log
- selftest: runqemu: use better error message when asserts fail
- shadow: Fix can not print full login timeout message
- staging/multilib: Fix manifest corruption
- staging: Separate out different multiconfig manifests
- sudo: upgrade to 1.9.13p3
- systemd.bbclass: Add /usr/lib/systemd to searchpaths as well
- systemd: add group sgx to udev package
- systemd: fix wrong nobody-group assignment
- timezone: use 'tz' subdir instead of \${WORKDIR} directly
- toolchain-scripts: Handle spaces within user \$PATH
- tzcode-native: fix build with gcc-13 on host
- tzdata: upgrade to 2023c
- tzdata: use separate *B* instead of *WORKDIR* for zic output
- u-boot: Map arm64 into map for u-boot dts installation
- uninative: Upgrade to 3.9 to include glibc 2.37
- vala: Fix install conflict when enable multilib.
- vim: add missing pkgconfig inherit
- vim: set modified-by to the recipe *MAINTAINER*
- vim: upgrade to 9.0.1429
- xcb-proto: Fix install conflict when enable multilib.

### **Known Issues in Yocto-4.1.4**

- N/A

### **Contributors to Yocto-4.1.4**

- Alexander Kanavin
- Andrew Geissler
- Arturo Buzarra
- Bhabu Bindu
- Bruce Ashfield
- Carlos Alberto Lopez Perez
- Chee Yang Lee
- Chris Elledge
- Christoph Lauer
- Dmitry Baryshkov
- Enrico Jörns
- Fawzi KHABER
- Frank de Brabander
- Frederic Martinsons
- Geoffrey GIRY
- Hitendra Prajapati
- Jose Quaresma
- Kenfe-Mickael Laventure
- Khem Raj
- Marek Vasut
- Martin Jansa
- Michael Halstead
- Michael Opdenacker
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Narpat Mali
- Pavel Zhukov
- Peter Marko

- Piotr Łobacz
- Randy MacLeod
- Richard Purdie
- Robert Yang
- Romuald JEANNE
- Romuald Jeanne
- Ross Burton
- Siddharth
- Siddharth Doshi
- Soumya
- Steve Sakoman
- Sudip Mukherjee
- Tim Orling
- Tobias Hagelborn
- Tom Hochstein
- Trevor Woerner
- Wang Mingyu
- Xiangyu Chen
- Zoltan Boszormenyi

## Repositories / Downloads for Yocto-4.1.4

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [langdale](#)
- Tag: [yocto-4.1.4](#)
- Git Revision: [3e95f268ce04b49ba6731fd4bbc53b1693c21963](#)
- Release Artefact: [poky-3e95f268ce04b49ba6731fd4bbc53b1693c21963](#)
- sha: [54798c4b519f5e11f409e1fd074bea1bc0a1b80672aa60dddbac772c8e4d838b](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.4/poky-3e95f268ce04b49ba6731fd4bbc53b1693c21963.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.4/poky-3e95f268ce04b49ba6731fd4bbc53b1693c21963.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [langdale](#)

- Tag: `yocto-4.1.4`
- Git Revision: `78211cda40eb018a3aa535c75b61e87337236628`
- Release Artefact: `oecore-78211cda40eb018a3aa535c75b61e87337236628`
- sha: `1303d836bae54c438c64d6b9f068eb91c32be4cc1779e89d0f2d915a55d59b15`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.4/oecore-78211cda40eb018a3aa535c75b61e87337236628.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.4/oecore-78211cda40eb018a3aa535c75b61e87337236628.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `langdale`
- Tag: `yocto-4.1.4`
- Git Revision: `b0067202db8573df3d23d199f82987cebe1bee2c`
- Release Artefact: `meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c`
- sha: `704f2940322b81ce774e9cbd27c3fa843111d497dc7b1eaa39cd694d9a2366`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.4/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.4/meta-mingw-b0067202db8573df3d23d199f82987cebe1bee2c.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.2`
- Tag: `yocto-4.1.4`
- Git Revision: `5b105e76dd7de3b9a25b17b397f2c12c80048894`
- Release Artefact: `bitbake-5b105e76dd7de3b9a25b17b397f2c12c80048894`
- sha: `2cd6448138816f5a906f9927c6b6fdc5cf24981ef32b6402312f52ca490edb4f`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.1.4/bitbake-5b105e76dd7de3b9a25b17b397f2c12c80048894.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.1.4/bitbake-5b105e76dd7de3b9a25b17b397f2c12c80048894.tar.bz2>

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `langdale`
- Tag: `yocto-4.1.4`
- Git Revision: `da685fc5e69d49728e3ffd6c4d623e7e1745059d`



## 17.11 Release 4.0 (kirkstone)

### 17.11.1 Release 4.0 (kirkstone)

#### Migration notes for 4.0 (kirkstone)

This section provides migration information for moving to the Yocto Project 4.0 Release (codename "kirkstone") from the prior release.

#### Inclusive language improvements

To use more [inclusive language](#) in the code and documentation, some variables have been renamed, and some have been deleted where they are no longer needed. In many cases the new names are also easier to understand. BitBake will stop with an error when renamed or removed variables still exist in your recipes or configuration.

Please note that the change applies also to environmental variables, so make sure you use a fresh environment for your build.

The following variables have changed their names:

- `BB_ENV_WHITELIST` became `BB_ENV_PASSTHROUGH`
- `BB_ENV_EXTRAWHITE` became `BB_ENV_PASSTHROUGH_ADDITIONS`
- `BB_HASHBASE_WHITELIST` became `BB_BASEHASH_IGNORE_VARS`
- `BB_HASHCONFIG_WHITELIST` became `BB_HASHCONFIG_IGNORE_VARS`
- `BB_HASHTASK_WHITELIST` became `BB_TASKHASH_IGNORE_TASKS`
- `BB_SETSCENE_ENFORCE_WHITELIST` became `BB_SETSCENE_ENFORCE_IGNORE_TASKS`
- `CVE_CHECK_PN_WHITELIST` became `CVE_CHECK_SKIP_RECIPE`
- `CVE_CHECK_WHITELIST` became `CVE_CHECK_IGNORE`
- `ICECC_USER_CLASS_BL` became `ICECC_CLASS_DISABLE`
- `ICECC_SYSTEM_CLASS_BL` became `ICECC_CLASS_DISABLE`
- `ICECC_USER_PACKAGE_WL` became `ICECC_RECIPE_ENABLE`
- `ICECC_USER_PACKAGE_BL` became `ICECC_RECIPE_DISABLE`
- `ICECC_SYSTEM_PACKAGE_BL` became `ICECC_RECIPE_DISABLE`
- `LICENSE_FLAGS_WHITELIST` became `LICENSE_FLAGS_ACCEPTED`
- `MULTI_PROVIDER_WHITELIST` became `BB_MULTI_PROVIDER_ALLOWED`
- `PNBLACKLIST` became `SKIP_RECIPE`
- `SDK_LOCAL_CONF_BLACKLIST` became `ESDK_LOCALCONF_REMOVE`
- `SDK_LOCAL_CONF_WHITELIST` became `ESDK_LOCALCONF_ALLOW`
- `SDK_INHERIT_BLACKLIST` became `ESDK_CLASS_INHERIT_DISABLE`
- `SSTATE_DUPWHITELIST` became `SSTATE_ALLOW_OVERLAP_FILES`

- `SYSROOT_DIRS_BLACKLIST` became *`SYSROOT_DIRS_IGNORE`*
- `UNKNOWN_CONFIGURE_WHITELIST` became *`UNKNOWN_CONFIGURE_OPT_IGNORE`*
- `WHITELIST_<license>` became *`INCOMPATIBLE_LICENSE_EXCEPTIONS`*

In addition, `BB_STAMP_WHITELIST`, `BB_STAMP_POLICY`, `INHERIT_BLACKLIST`, `TUNEABI`, `TUNEABI_WHITELIST`, and `TUNEABI_OVERRIDE` have been removed.

Many internal variable names have been also renamed accordingly.

In addition, in the `cve-check` output, the CVE issue status `Whitelisted` has been renamed to `Ignored`.

The *`BB_DISKMON_DIRS`* variable value now uses the term `HALT` instead of `ABORT`.

A *`convert-variable-renames.py`* script is provided to convert your recipes and configuration, and also warns you about the use of problematic words. The script performs changes and you need to review them before committing. An example warning looks like:

```
poky/scripts/lib/devtool/upgrade.py needs further work at line 275 since it_
↳ contains abort
```

## Fetching changes

- Because of the uncertainty in future default branch names in git repositories, it is now required to add a branch name to all URLs described by `git://` and `git+ssh://` *`SRC_URI`* entries. For example:

```
SRC_URI = "git://git.denx.de/u-boot.git;branch=master"
```

A *`convert-srcuri`* script to convert your recipes is available in *`OpenEmbedded-Core (OE-Core)`* and in *`Poky`*.

- Because of *`GitHub dropping support for the git: protocol`*, recipes now need to use `;protocol=https` at the end of GitHub URLs. The same *`convert-srcuri`* script mentioned above can be used to convert your recipes.
- Network access from tasks is now disabled by default on kernels which support this feature (on most recent distros such as CentOS 8 and Debian 11 onwards). This means that tasks accessing the network need to be marked as such with the `network` flag. For example:

```
do_mytask[network] = "1"
```

This is allowed by default from *`do_fetch`* but not from any of our other standard tasks. Recipes shouldn't be accessing the network outside of *`do_fetch`* as it usually undermines fetcher source mirroring, image and licence manifests, software auditing and supply chain security.

## License changes

- The ambiguous "BSD" license has been removed from the `common-licenses` directory. Each recipe that fetches or builds BSD-licensed code should specify the proper version of the BSD license in its *`LICENSE`* value.
- *`LICENSE`* variable values should now use *`SPDX identifiers`*. If they do not, by default a warning will be shown. A *`convert-spdx-licenses.py`* script can be used to update your recipes.

- *INCOMPATIBLE\_LICENSE* should now use *SPDX* identifiers. Additionally, wildcarding is now limited to specifically supported values - see the *INCOMPATIBLE\_LICENSE* documentation for further information.
- The *AVAILABLE\_LICENSES* variable has been removed. This variable was a performance liability and is highly dependent on which layers are added to the configuration, which can cause signature issues for users. In addition the `available_licenses()` function has been removed from the *license* class as it is no longer needed.

## Removed recipes

The following recipes have been removed in this release:

- *dbus-test*: merged into main *dbus* recipe
- *libid3tag*: moved to *meta-oe* - no longer needed by anything in OE-Core
- *libportal*: moved to *meta-gnome* - no longer needed by anything in OE-Core
- *linux-yocto*: removed version 5.14 recipes (5.15 and 5.10 still provided)
- *python3-nose*: has not changed since 2016 upstream, and no longer needed by anything in OE-Core
- *rustfmt*: not especially useful as a standalone recipe

## Python changes

- *distutils* has been deprecated upstream in Python 3.10 and thus the *distutils\** classes have been moved to *meta-python*. Recipes that inherit the *distutils\** classes should be updated to inherit *setuptools\** equivalents instead.
- The Python package build process is now based on *wheels*. The new Python packaging classes that should be used are *python\_flit\_core*, *python\_setuptools\_build\_meta* and *python\_poetry\_core*.
- The *setuptools3* class *do\_install* task now installs the *wheel* binary archive. In current versions of *setuptools* the legacy `setup.py install` method is deprecated. If the `setup.py` cannot be used with *wheels*, for example it creates files outside of the Python module or standard entry points, then *setuptools3\_legacy* should be used instead.

## Prelink removed

Prelink has been dropped by *glibc* upstream in 2.36. It already caused issues with binary corruption, has a number of open bugs and is of questionable benefit without disabling load address randomization and PIE executables.

We disabled prelinking by default in the honister (3.4) release, but left it able to be enabled if desired. However, without *glibc* support it cannot be maintained any further, so all of the prelinking functionality has been removed in this release. If you were enabling the *image-prelink* class in *INHERIT*, *IMAGE\_CLASSES*, *USER\_CLASSES* etc in your configuration, then you will need to remove the reference(s).

## Reproducible as standard

Reproducibility is now considered as standard functionality, thus the `reproducible` class has been removed and its previous contents merged into the `base` class. If you have references in your configuration to `reproducible` in `INHERIT`, `USER_CLASSES` etc. then they should be removed.

Additionally, the `BUILD_REPRODUCIBLE_BINARIES` variable is no longer used. Specifically for the kernel, if you wish to enable build timestamping functionality that is normally disabled for reproducibility reasons, you can do so by setting a new `KERNEL_DEBUG_TIMESTAMPS` variable to "1".

## Supported host distribution changes

- Support for [AlmaLinux](#) hosts replacing [CentOS](#). The following distribution versions were dropped: CentOS 8, Ubuntu 16.04 and Fedora 30, 31 and 32.
- `gcc` version 7.5 is now required at minimum on the build host. For older host distributions where this is not available, you can use the `buildtools-extended` tarball (easily installable using `scripts/install-buildtools`).

## :append/:prepend in combination with other operators

The `append`, `prepend` and `remove` operators can now only be combined with `=` and `:=` operators. To the exception of the `append` plus `+=` and `prepend` plus `+=` combinations, all combinations could be factored up to the `append`, `prepend` or `remove` in the combination. This brought a lot of confusion on how the override style syntax operators work and should be used. Therefore, those combinations should be replaced by a single `append`, `prepend` or `remove` operator without any additional change. For the `append` plus `+=` (and `prepend` plus `+=`) combinations, the content should be prefixed (respectively suffixed) by a space to maintain the same behavior. You can learn more about override style syntax operators (`append`, `prepend` and `remove`) in the BitBake documentation: [Appending and Prepending \(Override Style Syntax\)](#) and [Removal \(Override Style Syntax\)](#).

## Miscellaneous changes

- `blacklist.bbclass` is removed and the functionality moved to the `base` class with a more descriptive `var-flag` variable named `SKIP_RECIPE` which will use the `bb.parse.SkipRecipe()` function. The usage remains the same, for example:

```
SKIP_RECIPE[my-recipe] = "Reason for skipping recipe"
```

- `allarch` packagegroups can no longer depend on packages which use `PKG` renaming such as `debian`. Such packagegroups recipes should be changed to avoid inheriting `allarch`.
- The `lnr` script has been removed. `lnr` implemented the same behaviour as `ln --relative --symbolic`, since at the time of creation `--relative` was only available in `coreutils` 8.16 onwards which was too new for the older supported distros. Current supported host distros have a new enough version of `coreutils`, so it is no longer needed. If you have any calls to `lnr` in your recipes or classes, they should be replaced with `ln --relative --symbolic` or `ln -rs` if you prefer the short version.
- The `package_qa_handle_error()` function formerly in the `insane` class has been moved and renamed - if you have any references in your own custom classes they should be changed to `oe.qa.handle_error()`.

- When building `perl`, Berkeley db support is no longer enabled by default, since Berkeley db is largely obsolete. If you wish to reenable it, you can append `bdb` to `PACKAGECONFIG` in a `perl` `bbappend` or `PACKAGECONFIG:pn-perl` at the configuration level.
- For the `xserver-xorg` recipe, the `xshmfence`, `xmlto` and `systemd` options previously supported in `PACKAGECONFIG` have been removed, as they are no longer supported since the move from building it with `autotools` to `meson` in this release.
- For the `libsd12` recipe, various X11 features are now disabled by default (primarily for reproducibility purposes in the native case) with options in `EXTRA_OECMAKE` within the recipe. These can be changed within a `bbappend` if desired. See the `libsd12` recipe for more details.
- The `cortexa72-crc` and `cortexa72-crc-crypto` tunes have been removed since the `crc` extension is now enabled by default for `cortexa72`. Replace any references to these with `cortexa72` and `cortexa72-crypto` respectively.
- The Python development shell (previously known as `devpyshell`) feature has been renamed to `pydevshell`. To start it you should now run:

```
bitbake <target> -c pydevshell
```

- The `packagegroups-core-full-cmdline-libs` packagegroup is no longer produced, as libraries should normally be brought in via dependencies. If you have any references to this then remove them.
- The `TOPDIR` variable and the current working directory are no longer modified when parsing recipes. Any code depending on the previous behaviour will no longer work - change any such code to explicitly use appropriate path variables instead.
- In order to exclude the kernel image from the image roots, `RRECOMMENDS: ${KERNEL_PACKAGE_NAME}-base` should be set instead of `RDEPENDS: ${KERNEL_PACKAGE_NAME}-base`.

### 17.11.2 Release notes for 4.0 (kirkstone)

This is a Long Term Support release, published in April 2022, and supported at least for two years (April 2024).

#### New Features / Enhancements in 4.0

- Linux kernel 5.15, glibc 2.35 and ~300 other recipe upgrades
- Reproducibility: this release fixes the reproducibility issues with `rust-llvm` and `golang`. Recipes in `OpenEmbedded-Core` are now fully reproducible. Functionality previously in the optional "reproducible" class has been merged into the `base` class.
- Network access is now disabled by default for tasks other than where it is expected to ensure build integrity (where host kernel supports it)
- The Yocto Project now allows you to reuse the Shared State cache from its autobuilder. If the network connection between our server and your machine is faster than you would build recipes from source, you can try to speed up your builds by using such Shared State and Hash Equivalence by setting:

```
BB_SIGNATURE_HANDLER = "OEEquivHash"
BB_HASHSERVE = "auto"
BB_HASHSERVE_UPSTREAM = "hashserv.yoctoproject.org:8686"
SSTATE_MIRRORS ?= "file://.* https://sstate.yoctoproject.org/all/PATH;
↳downloadfilename=PATH"
```

- The Python package build process is now based on [wheels](#) in line with the upstream direction.
- New *overlayfs* and *overlayfs-etc* classes and `overlayroot` support in the *Initramps* framework to make it easier to overlay read-only filesystems (for example) with [OverlayFS](#).
- Inclusive language adjustments to some variable names - see the [4.0 migration guide](#) for details.

- New recipes:

- buildtools-docs-tarball
- libptytty
- libxcvt
- lua
- nghttp2
- python3-alabaster
- python3-asn1crypto
- python3-babel
- python3-bcrypt
- python3-certifi
- python3-cffi
- python3-chardet
- python3-cryptography
- python3-cryptography-vectors
- python3-dtschema
- python3-flit-core
- python3-idna
- python3-imagesize
- python3-installer
- python3-iso8601
- python3-jsonpointer
- python3-jsonschema
- python3-ndg-httpsclient

- python3-ply
- python3-poetry-core
- python3-pretend
- python3-psutil
- python3-pyasnl
- python3-pycparser
- python3-pyopenssl
- python3-pyrsistent
- python3-pysocks
- python3-pytest-runner
- python3-pytest-subtests
- python3-pytz
- python3-requests
- python3-rfc3339-validator
- python3-rfc3986-validator
- python3-rfc3987
- python3-ruamel-yaml
- python3-semantic-version
- python3-setuptools-rust-native
- python3-snowballstemmer
- python3-sphinx
- python3-sphinxcontrib-applehelp
- python3-sphinxcontrib-devhelp
- python3-sphinxcontrib-htmlhelp
- python3-sphinxcontrib-jsmath
- python3-sphinxcontrib-qthelp
- python3-sphinxcontrib-serializinghtml
- python3-sphinx-rtd-theme
- python3-strict-rfc3339
- python3-tomli
- python3-typing-extensions
- python3-urllib3

- python3-vcversioner
- python3-webcolors
- python3-wheel
- repo
- seatd
- Extended recipes to native: wayland, wayland-protocols
- Shared state (sstate) improvements:
  - Switched to ZStandard (zstd) instead of Gzip, for better performance.
  - Allow validation of sstate signatures against a list of keys
  - Improved error messages and exception handling
- BitBake enhancements:
  - Fetcher enhancements:
    - \* New Crate Fetcher (crate://) for Rust packages
    - \* Added stripelevel support to unpack
    - \* git: Add a warning asking users to set a branch in git urls
    - \* git: Allow git fetcher to support subdir param
    - \* git: canonicalize ids in generated tarballs
    - \* git: stop generated tarballs from leaking info
    - \* npm: Put all downloaded files in the npm2 directory
    - \* npmsw: Add support for duplicate dependencies without url
    - \* npmsw: Add support for github prefix in npm shrinkwrap version
    - \* ssh: now supports checkstatus, allows : in URLs (both required for use with sstate) and no longer requires username
    - \* wget: add redirectauth parameter
    - \* wget: add 30s timeout for checkstatus calls
  - Show warnings for append/prepend/remove operators combined with +=/./=
  - Add bb.warnonce() and bb.erroronce() log methods
  - Improved setscene task display
  - Show elapsed time also for tasks with progress bars
  - Improved cleanup on forced shutdown (either because of errors or Ctrl+C)
  - contrib: Add Dockerfile for building PR service container
  - Change file format of siginfo files to use zstd compressed json
  - Display active tasks when printing keep-alive message to help debugging



- Architecture-specific enhancements:
  - ARM:
    - \* tune-cortexa72: Enable the crc extension by default for cortexa72
    - \* qemuarm64: Add tiny ktype to qemuarm64 bsp
    - \* armv9a/tune: Add the support for the Neoverse N2 core
    - \* arch-armv8-5a.inc: Add tune include for armv8.5a
    - \* grub-efi: Add xen\_boot support when 'xen' is in *DISTRO\_FEATURES* for aarch64
    - \* tune-cortexa73: Introduce cortexa73-crypto tune
    - \* libacpi: Build libacpi also for 'aarch64' machines
    - \* core-image-tiny-initramfs: Mark recipe as 32 bit ARM compatible
  - PowerPC:
    - \* weston-init: Use pixman rendering for qemuppc64
    - \* rust: add support for big endian 64-bit PowerPC
    - \* rust: Add snapshot checksums for powerpc64le
  - RISC-V:
    - \* libunwind: Enable for rv64
    - \* systemtap: Enable for riscv64
    - \* linux-yocto-dev: add qemuriscv32
    - \* packagegroup-core-tools-profile: Enable systemtap for riscv64
    - \* qemuriscv: Use virtio-tablet-pci for mouse
  - x86:
    - \* kernel-yocto: conditionally enable stack protection checking on x86-64
- Kernel-related enhancements:
  - Allow *Initramfs* to be built from a separate multiconfig
  - Make kernel-base recommend kernel-image, not depend (allowing images containing kernel modules without kernel image)
  - linux-yocto: split vtpm for more granular inclusion
  - linux-yocto: cfg/debug: add configs for kcsan
  - linux-yocto: cfg: add kcov feature fragment
  - linux-yocto: export pkgconfig variables to devshell
  - linux-yocto-dev: use versioned branch as default
  - New *KERNEL\_DEBUG\_TIMESTAMPS* variable (to replace removed *BUILD\_REPRODUCIBLE\_BINARIES* for the kernel)

- Introduce python3-dtschema-wrapper in preparation for mandatory schema checking on dtb files in 5.16
  - Allow disabling kernel artifact symlink creation
  - Allow changing default .bin kernel artifact extension
- FIT image related enhancements:
  - New `FIT_SUPPORTED_INITRAMFS_FSTYPES` variable to allow extending *Initramfs* image types to look for
  - New `FIT_CONF_PREFIX` variable to allow overriding FIT configuration prefix
  - Use 'bbnote' for better logging
- New *PACKAGECONFIG* options in `curl`, `dtc`, `epiphany`, `git`, `git`, `gststreamer1.0-plugins-bad`, `linux-yocto-dev`, `kmod`, `mesa`, `piglit`, `qemu`, `rpm`, `systemd`, `webkitgtk`, `weston-init`
- ptest enhancements in `findutils`, `lttng-tools`, `openssl`, `gawk`, `strace`, `lttng-tools`, `valgrind`, `perl`, `libxml-parser-perl`, `openssh`, `python3-cryptography`, `popt`
- Sysroot dependencies have been further optimised
- Significant effort to upstream / rationalise patches across a variety of recipes
- Allow the creation of block devices on top of UBI volumes
- archiver: new `ARCHIVER_MODE[compression]` to set tarball compression, and switch default to xz
- yocto-check-layer: add ability to perform tests from a global bbclass
- yocto-check-layer: improved README checks
- cve-check: add json output format
- cve-check: add coverage statistics on recipes with/without CVEs
- Added mirrors for kernel sources and uninative binaries on kernel.org
- glibc and binutils recipes now use shallow mirror tarballs for faster fetching
- When patching fails, show more information on the fatal error
- wic Image Creator enhancements:
  - Support rootdev identified by partition label
- rawcopy: Add support for packed images
- partition: Support valueless keys in sourceparams
- QA check enhancements:
  - Allow treating license issues as errors
  - Added a check that Upstream-Status patch tag is present and correctly formed
  - Added a check for directories that are expected to be empty
  - Ensure addition of patch-fuzz retriggers `do_qa_patch`
  - Added a sanity check for allarch packagegroups

- *create-spdx* class improvements:
  - Get SPDX-License-Identifier from source files
  - Generate manifest also for SDKs
  - New SPDX\_ORG variable to allow changing the Organization field value
  - Added packageSupplier field
  - Added create\_annotation function
- devtool add / recipetool create enhancements:
  - Extend curl detection when creating recipes
  - Handle GitLab URLs like we do GitHub
  - Recognize more standard license text variants
  - Separate licenses with & operator
  - Detect more known licenses in Python code
  - Move license md5sums data into CSV files
  - npm: Use README as license fallback
- SDK-related enhancements:
  - Extended recipes to *nativesdk*: cargo, librsvg, libstd-rs, libva, python3-docutil, python3-packaging
  - Enabled *nativesdk* recipes to find a correct version of the rust cross compiler
  - Support creating per-toolchain cmake file in SDK
- Rust enhancements:
  - New python\_setuptools3\_rust class to enable building python extensions in Rust
  - classes/meson: Add optional rust definitions
- QEMU / runqemu enhancements:
  - qemu: Add knob for enabling PMDK pmem support
  - qemu: add tpm string section to qemu acpi table
  - qemu: Build on musl targets
  - runqemu: support rootfs mounted ro
  - runqemu: add *DEPLOY\_DIR\_IMAGE* replacement in QB\_OPT\_APPEND
  - runqemu: Allow auto-detection of the correct graphics options
- Capped `cpu_count()` (used to set parallelisation defaults) to 64 since any higher usually hurts parallelisation
- Adjust some GL-using recipes so that they only require virtual/egl
- package\_rpm: use zstd instead of xz
- npm: new EXTRA\_OENPM variable (to set node-gyp variables for example)

- npm: new `NPM_NODEDIR` variable
- perl: Enable threading
- u-boot: Convert `${UBOOT_ENV}.cmd` into `${UBOOT_ENV}.scr`
- u-boot: Split `do_configure` logic into separate file
- go.bbclass: Allow adding parameters to `go ldflags`
- go: log build id computations
- scons: support out-of-tree builds
- scripts: Add a conversion script to use SPDX license names
- scripts: Add `convert-variable-renames` script for inclusive language variable renaming
- binutils-cross-canadian: enable gold for mingw
- grub-efi: Add option to include all available modules
- bitbake.conf: allow wayland distro feature through for native/SDK builds
- weston-init: Pass `--continue-without-input` when launching weston
- weston: wrapper for weston modules argument
- weston: Add a knob to control simple clients
- uninative: Add version to uninative tarball name
- volatile-binds: SELinux and overlayfs extensions in `mount-copybind`
- gtk-icon-cache: Allow using gtk4
- kmod: Add an exclude directive to `depmod`
- os-release: add `os-release-initrd` package for use in systemd-based *Initramfs* images
- gstreamer1.0-plugins-base: add support for graphene
- gpg-sign: Add parameters to gpg signature function
- package\_manager: sign DEB package feeds
- zstd: add `libzstd` package
- libical: build gobject and vala introspection
- dhcpcd: add option to set `DBDIR` location
- rpcbind: install `rpcbind.conf`
- mdadm: install `mdcheck`
- boost: add json lib
- libxkbcommon: allow building of API documentation
- libxkbcommon: split libraries and `xkbcli` into separate packages
- systemd: move systemd shared library into its own package

- systemd: Minimize udev package size if `DISTRO_FEATURES` doesn't contain sysvinit

### Known Issues in 4.0

- `make` version 4.2.1 is known to be buggy on non-Ubuntu systems. If this `make` version is detected on host distributions other than Ubuntu at build start time, then a warning will be displayed.

### Recipe License changes in 4.0

The following corrections have been made to the `LICENSE` values set by recipes:

- `cmake`: add BSD-1-Clause & MIT & BSD-2-Clause to `LICENSE` due to additional vendored libraries in native/target context
- `gettext`: extend `LICENSE` conditional upon `PACKAGECONFIG` (due to vendored libraries)
- `gstreamer1.0`: update licenses of all modules to LGPL-2.1-or-later (with some exceptions that are GPL-2.0-or-later)
- `gstreamer1.0-plugins-bad/ugly`: use the GPL-2.0-or-later only when it is in use
- `kern-tools-native`: add missing MIT license due to Kconfiglib
- `libcap`: add `pam_cap` license to `LIC_FILES_CHKSUM` if `pam` is enabled
- `libidn2`: add Unicode-DFS-2016 license
- `libSDL2`: add BSD-2-Clause to `LICENSE` due to default `yuv2rgb` and `hidapi` inclusion
- `libx11-compose-data`: update `LICENSE` to "MIT & MIT-style & BSD-1-Clause & HPND & HPND-sell-variant" to better reflect reality
- `libx11`: update `LICENSE` to "MIT & MIT-style & BSD-1-Clause & HPND & HPND-sell-variant" to better reflect reality
- `libxshmfence`: correct `LICENSE` - MIT -> HPND
- `newlib`: add BSD-3-Clause to `LICENSE`
- `python3-idna`: correct `LICENSE` - Unicode -> Unicode-TOU
- `python3-pip`: add "Apache-2.0 & MPL-2.0 & LGPL-2.1-only & BSD-3-Clause & PSF-2.0 & BSD-2-Clause" to `LICENSE` due to vendored libraries

Other license-related notes:

- The ambiguous "BSD" license has been removed from the `common-licenses` directory. Each recipe that fetches or builds BSD-licensed code should specify the proper version of the BSD license in its `LICENSE` value.
- `LICENSE` definitions now have to use `SPDX` identifiers. A `convert-spdx-licenses.py` script can be used to update your recipes.

## Security Fixes in 4.0

- binutils: CVE-2021-42574, CVE-2021-45078
- curl: CVE-2021-22945, CVE-2021-22946, CVE-2021-22947
- epiphany: CVE-2021-45085, CVE-2021-45086, CVE-2021-45087, CVE-2021-45088
- expat: CVE-2021-45960, CVE-2021-46143, CVE-2022-22822, CVE-2022-22823, CVE-2022-22824, CVE-2022-22825, CVE-2022-22826, CVE-2022-22827, CVE-2022-23852, CVE-2022-23990, CVE-2022-25235, CVE-2022-25236, CVE-2022-25313, CVE-2022-25314, CVE-2022-25315
- ffmpeg: CVE-2021-38114
- gcc: CVE-2021-35465, CVE-2021-42574, CVE-2021-46195, CVE-2022-24765
- glibc: CVE-2021-3998, CVE-2021-3999, CVE-2021-43396, CVE-2022-23218, CVE-2022-23219
- gmp: CVE-2021-43618
- go: CVE-2021-41771 and CVE-2021-41772
- grub2: CVE-2021-3981
- gzip: CVE-2022-1271
- libarchive : CVE-2021-31566, CVE-2021-36976
- libxml2: CVE-2022-23308
- libxslt: CVE-2021-30560
- lighttpd: CVE-2022-22707
- linux-yocto/5.10: amdgpu: CVE-2021-42327
- lua: CVE-2021-43396
- openssl: CVE-2021-4044, CVE-2022-0778
- qemu: CVE-2022-1050, CVE-2022-26353, CVE-2022-26354
- rpm: CVE-2021-3521
- seatd: CVE-2022-25643
- speex: CVE-2020-23903
- squashfs-tools: CVE-2021-41072
- systemd: CVE-2021-4034
- tiff: CVE-2022-0561, CVE-2022-0562, CVE-2022-0865, CVE-2022-0891, CVE-2022-0907, CVE-2022-0908, CVE-2022-0909, CVE-2022-0924, CVE-2022-1056, CVE-2022-22844
- unzip: CVE-2021-4217
- vim: CVE-2021-3796, CVE-2021-3872, CVE-2021-3875, CVE-2021-3927, CVE-2021-3928, CVE-2021-3968, CVE-2021-3973, CVE-2021-4187, CVE-2022-0128, CVE-2022-0156, CVE-2022-0158, CVE-2022-0261, CVE-2022-0318, CVE-2022-0319, CVE-2022-0554, CVE-2022-0696, CVE-2022-0714, CVE-2022-0729, CVE-2022-0943

- virglrenderer: [CVE-2022-0135](#), [CVE-2022-0175](#)
- webkitgtk: [CVE-2022-22589](#), [CVE-2022-22590](#), [CVE-2022-22592](#)
- xz: [CVE-2022-1271](#)
- zlib: [CVE-2018-25032](#)

## Recipe Upgrades in 4.0

- acpica: upgrade 20210730 -> 20211217
- acpid: upgrade 2.0.32 -> 2.0.33
- adwaita-icon-theme: update 3.34/38 -> 41.0
- alsa-ucm-conf: upgrade 1.2.6.2 -> 1.2.6.3
- alsa: upgrade 1.2.5 -> 1.2.6
- apt: upgrade 2.2.4 -> 2.4.3
- asciidoc: upgrade 9.1.0 -> 10.0.0
- atk: upgrade 2.36.0 -> 2.38.0
- at-spi2-core: upgrade 2.40.3 -> 2.42.0
- at: update 3.2.2 -> 3.2.5
- autoconf-archive: upgrade 2021.02.19 -> 2022.02.11
- automake: update 1.16.3 -> 1.16.5
- bash: upgrade 5.1.8 -> 5.1.16
- bind: upgrade 9.16.20 -> 9.18.1
- binutils: Bump to latest 2.38 release branch
- bison: upgrade 3.7.6 -> 3.8.2
- bluez5: upgrade 5.61 -> 5.64
- boost: update 1.77.0 -> 1.78.0
- btrfs-tools: upgrade 5.13.1 -> 5.16.2
- buildtools-installer: Update to use 3.4
- busybox: 1.34.0 -> 1.35.0
- ca-certificates: update 20210119 -> 20211016
- cantarell-fonts: update 0.301 -> 0.303.1
- ccache: upgrade 4.4 -> 4.6
- cmake: update 3.21.1 -> 3.22.3
- connman: update 1.40 -> 1.41
- coreutils: update 8.32 -> 9.0

- cracklib: update 2.9.5 -> 2.9.7
- createrepo-c: upgrade 0.17.4 -> 0.19.0
- cronie: upgrade 1.5.7 -> 1.6.0
- cups: update 2.3.3op2 -> 2.4.1
- curl: update 7.78.0 -> 7.82.0
- dbus: upgrade 1.12.20 -> 1.14.0
- debianutils: update 4.11.2 -> 5.7
- dhcpcd: upgrade 9.4.0 -> 9.4.1
- diffoscope: upgrade 181 -> 208
- dnf: upgrade 4.8.0 -> 4.11.1
- dpkg: update 1.20.9 -> 1.21.4
- e2fsprogs: upgrade 1.46.4 -> 1.46.5
- ed: upgrade 1.17 -> 1.18
- efivar: update 37 -> 38
- elfutils: update 0.185 -> 0.186
- ell: upgrade 0.43 -> 0.49
- enchant2: upgrade 2.3.1 -> 2.3.2
- epiphany: update 40.3 -> 42.0
- erofs-utils: update 1.3 -> 1.4
- ethtool: update to 5.16
- expat: upgrade 2.4.1 -> 2.4.7
- ffmpeg: update 4.4 -> 5.0
- file: upgrade 5.40 -> 5.41
- findutils: upgrade 4.8.0 -> 4.9.0
- flac: upgrade 1.3.3 -> 1.3.4
- freetype: upgrade 2.11.0 -> 2.11.1
- fribidi: upgrade 1.0.10 -> 1.0.11
- gawk: update 5.1.0 -> 5.1.1
- gcompat: Update to latest
- gdbm: upgrade 1.19 -> 1.23
- gdb: Upgrade to 11.2
- ghostscript: update 9.54.0 -> 9.55.0



- gi-docgen: upgrade 2021.7 -> 2022.1
- git: update 2.33.0 -> 2.35.2
- glib-2.0: update 2.68.4 -> 2.72.0
- glibc: Upgrade to 2.35
- glib-networking: update 2.68.2 -> 2.72.0
- glslang: update 11.5.0 -> 11.8.0
- gnu-config: update to latest revision
- gnupg: update 2.3.1 -> 2.3.4
- gnutls: update 3.7.2 -> 3.7.4
- gobject-introspection: upgrade 1.68.0 -> 1.72.0
- go-helloworld: update to latest revision
- go: update 1.16.7 -> 1.17.8
- gpgme: upgrade 1.16.0 -> 1.17.1
- gsettings-desktop-schemas: upgrade 40.0 -> 42.0
- gst-devtools: 1.18.4 -> 1.20.1
- gst-examples: 1.18.4 -> 1.18.6
- gstreamer1.0: 1.18.4 -> 1.20.1
- gstreamer1.0-libav: 1.18.4 -> 1.20.1
- gstreamer1.0-omx: 1.18.4 -> 1.20.1
- gstreamer1.0-plugins-bad: 1.18.4 1.20.1
- gstreamer1.0-plugins-base: 1.18.4 -> 1.20.1
- gstreamer1.0-plugins-good: 1.18.4 -> 1.20.1
- gstreamer1.0-plugins-ugly: 1.18.4 -> 1.20.1
- gstreamer1.0-python: 1.18.4 -> 1.20.1
- gstreamer1.0-rtsp-server: 1.18.4 -> 1.20.1
- gstreamer1.0-vaapi: 1.18.4 -> 1.20.1
- gtk+3: upgrade 3.24.30 -> 3.24.33
- gzip: upgrade 1.10 -> 1.12
- harfbuzz: upgrade 2.9.0 -> 4.0.1
- hdparm: upgrade 9.62 -> 9.63
- help2man: upgrade 1.48.4 -> 1.49.1
- icu: update 69.1 -> 70.1

- ifupdown: upgrade 0.8.36 -> 0.8.37
- inetutils: update 2.1 -> 2.2
- init-system-helpers: upgrade 1.60 -> 1.62
- iproute2: update to 5.17.0
- iputils: update 20210722 to 20211215
- iso-codes: upgrade 4.6.0 -> 4.9.0
- itstool: update 2.0.6 -> 2.0.7
- iw: upgrade 5.9 -> 5.16
- json-glib: upgrade 1.6.4 -> 1.6.6
- kea: update 1.8.2 -> 2.0.2
- kexec-tools: update 2.0.22 -> 2.0.23
- less: upgrade 590 -> 600
- libarchive: upgrade 3.5.1 -> 3.6.1
- libatomic-ops: upgrade 7.6.10 -> 7.6.12
- libbsd: upgrade 0.11.3 -> 0.11.5
- libcap: update 2.51 -> 2.63
- libcgrouper: upgrade 2.0 -> 2.0.1
- libcomps: upgrade 0.1.17 -> 0.1.18
- libconvert-asn1-perl: upgrade 0.31 -> 0.33
- libdazzle: upgrade 3.40.0 -> 3.44.0
- libdnf: update 0.63.1 -> 0.66.0
- libdrm: upgrade 2.4.107 -> 2.4.110
- libedit: upgrade 20210714-3.1 -> 20210910-3.1
- liberation-fonts: update 2.1.4 -> 2.1.5
- libevdev: upgrade 1.11.0 -> 1.12.1
- libexif: update 0.6.22 -> 0.6.24
- libgit2: update 1.1.1 -> 1.4.2
- libgpg-error: update 1.42 -> 1.44
- libhandy: update 1.2.3 -> 1.5.0
- libical: upgrade 3.0.10 -> 3.0.14
- libinput: update to 1.19.3
- libjitterentropy: update 3.1.0 -> 3.4.0

- libjpeg-turbo: upgrade 2.1.1 -> 2.1.3
- libmd: upgrade 1.0.3 -> 1.0.4
- libmicrohttpd: upgrade 0.9.73 -> 0.9.75
- libmodulemd: upgrade 2.13.0 -> 2.14.0
- libpam: update 1.5.1 -> 1.5.2
- libpcrc2: upgrade 10.37 -> 10.39
- libpipeline: upgrade 1.5.3 -> 1.5.5
- librepo: upgrade 1.14.1 -> 1.14.2
- librsvg: update 2.40.21 -> 2.52.7
- libsamplerate0: update 0.1.9 -> 0.2.2
- libSDL2: update 2.0.16 -> 2.0.20
- libseccomp: update to 2.5.3
- libsecret: upgrade 0.20.4 -> 0.20.5
- libsndfile1: bump to version 1.0.31
- libsolv: upgrade 0.7.19 -> 0.7.22
- libsoup-2.4: upgrade 2.72.0 -> 2.74.2
- libsoup: add a recipe for 3.0.5
- libssh2: update 1.9.0 -> 1.10.0
- libtasn1: upgrade 4.17.0 -> 4.18.0
- libtool: Upgrade 2.4.6 -> 2.4.7
- libucontext: Upgrade to 1.2 release
- libunistring: update 0.9.10 -> 1.0
- libunwind: upgrade 1.5.0 -> 1.6.2
- liburcu: upgrade 0.13.0 -> 0.13.1
- libusb1: upgrade 1.0.24 -> 1.0.25
- libuv: update 1.42.0 -> 1.44.1
- libva: update 2.12.0 -> 2.14.0
- libva-utils: upgrade 2.13.0 -> 2.14.0
- libwebp: 1.2.1 -> 1.2.2
- libwpe: upgrade 1.10.1 -> 1.12.0
- libx11: update to 1.7.3.1
- libxcrypt: upgrade 4.4.26 -> 4.4.27

- libxcrypt-compat: upgrade 4.4.26 -> 4.4.27
- libxi: update to 1.8
- libxkbcommon: update to 1.4.0
- libxml2: update to 2.9.13
- libxslt: update to v1.1.35
- lighttpd: update 1.4.59 -> 1.4.64
- linux-firmware: upgrade 20210818 -> 20220310
- linux-libc-headers: update to v5.16
- linux-yocto/5.10: update to v5.10.109
- linux-yocto/5.15: introduce recipes (v5.15.32)
- linux-yocto-dev: update to v5.18+
- linux-yocto-rt/5.10: update to -rt61
- linux-yocto-rt/5.15: update to -rt34
- llvm: update 12.0.1 -> 13.0.1
- logrotate: update 3.18.1 -> 3.19.0
- lsof: update 4.91 -> 4.94.0
- ltp: update 20210927 -> 20220121
- ltp: Update to 20210927
- ltng-modules: update devupstream to latest 2.13
- ltng-modules: update to 2.13.3
- ltng-tools: upgrade 2.13.0 -> 2.13.4
- ltng-ust: upgrade 2.13.0 -> 2.13.2
- lua: update 5.3.6 -> 5.4.4
- lzip: upgrade 1.22 -> 1.23
- man-db: upgrade 2.9.4 -> 2.10.2
- man-pages: update to 5.13
- mdadm: update 4.1 -> 4.2
- mesa: upgrade 21.2.1 -> 22.0.0
- meson: update 0.58.1 -> 0.61.3
- minicom: Upgrade 2.7.1 -> 2.8
- mmc-utils: upgrade to latest revision
- mobile-broadband-provider-info: upgrade 20210805 -> 20220315

- mpg123: upgrade 1.28.2 -> 1.29.3
- msmtmp: upgrade 1.8.15 -> 1.8.20
- mtd-utils: upgrade 2.1.3 -> 2.1.4
- mtools: upgrade 4.0.35 -> 4.0.38
- musl: Update to latest master
- ncurses: update 6.2 -> 6.3
- newlib: Upgrade 4.1.0 -> 4.2.0
- nfs-utils: upgrade 2.5.4 -> 2.6.1
- nhttp2: upgrade 1.45.1 -> 1.47.0
- ofono: upgrade 1.32 -> 1.34
- opensbi: Upgrade to 1.0
- openssh: upgrade 8.7p1 -> 8.9
- openssl: update 1.1.1i -> 3.0.2
- opkg: upgrade 0.4.5 -> 0.5.0
- opkg-utils: upgrade 0.4.5 -> 0.5.0
- ovmf: update 202105 -> 202202
- p11-kit: update 0.24.0 -> 0.24.1
- pango: upgrade 1.48.9 -> 1.50.4
- patchelf: upgrade 0.13 -> 0.14.5
- perl-cross: update 1.3.6 -> 1.3.7
- perl: update 5.34.0 -> 5.34.1
- piglit: upgrade to latest revision
- pigz: upgrade 2.6 -> 2.7
- pinentry: update 1.1.1 -> 1.2.0
- pkgconfig: Update to latest
- psplash: upgrade to latest revision
- puzzles: upgrade to latest revision
- python3-asn1crypto: upgrade 1.4.0 -> 1.5.1
- python3-attrs: upgrade 21.2.0 -> 21.4.0
- python3-cryptography: Upgrade to 36.0.2
- python3-cryptography-vectors: upgrade to 36.0.2
- python3-cython: upgrade 0.29.24 -> 0.29.28

- python3-dbusmock: update to 0.27.3
- python3-docutils: upgrade 0.17.1 0.18.1
- python3-dtschema: upgrade 2021.10 -> 2022.1
- python3-gitdb: upgrade 4.0.7 -> 4.0.9
- python3-git: update to 3.1.27
- python3-hypothesis: upgrade 6.15.0 -> 6.39.5
- python3-imagesize: upgrade 1.2.0 -> 1.3.0
- python3-importlib-metadata: upgrade 4.6.4 -> 4.11.3
- python3-jinja2: upgrade 3.0.1 -> 3.1.1
- python3-jsonschema: upgrade 3.2.0 -> 4.4.0
- python3-libarchive-c: upgrade 3.1 -> 4.0
- python3-magic: upgrade 0.4.24 -> 0.4.25
- python3-mako: upgrade 1.1.5 -> 1.1.6
- python3-markdown: upgrade 3.3.4 -> 3.3.6
- python3-markupsafe: upgrade 2.0.1 -> 2.1.1
- python3-more-itertools: upgrade 8.8.0 -> 8.12.0
- python3-numpy: upgrade 1.21.2 -> 1.22.3
- python3-packaging: upgrade 21.0 -> 21.3
- python3-pathlib2: upgrade 2.3.6 -> 2.3.7
- python3-pbr: upgrade 5.6.0 -> 5.8.1
- python3-pip: update 21.2.4 -> 22.0.3
- python3-pycairo: upgrade 1.20.1 -> 1.21.0
- python3-pycryptodome: upgrade 3.10.1 -> 3.14.1
- python3-pyelftools: upgrade 0.27 -> 0.28
- python3-pygments: upgrade 2.10.0 -> 2.11.2
- python3-pyobject: upgrade 3.40.1 -> 3.42.0
- python3-pyparsing: update to 3.0.7
- python3-pyrsistent: upgrade 0.18.0 -> 0.18.1
- python3-pytest-runner: upgrade 5.3.1 -> 6.0.0
- python3-pytest-subtests: upgrade 0.6.0 -> 0.7.0
- python3-pytest: upgrade 6.2.4 -> 7.1.1
- python3-pytz: upgrade 2021.3 -> 2022.1

- python3-py: upgrade 1.10.0 -> 1.11.0
- python3-pyyaml: upgrade 5.4.1 -> 6.0
- python3-ruamel-yaml: upgrade 0.17.16 -> 0.17.21
- python3-scons: upgrade 4.2.0 -> 4.3.0
- python3-setuptools-scm: upgrade 6.0.1 -> 6.4.2
- python3-setuptools: update to 59.5.0
- python3-smmap: update to 5.0.0
- python3-tomli: upgrade 1.2.1 -> 2.0.1
- python3: update to 3.10.3
- python3-urllib3: upgrade 1.26.8 -> 1.26.9
- python3-zipp: upgrade 3.5.0 -> 3.7.0
- qemu: update 6.0.0 -> 6.2.0
- quilt: upgrade 0.66 -> 0.67
- re2c: upgrade 2.2 -> 3.0
- readline: upgrade 8.1 -> 8.1.2
- repo: upgrade 2.17.3 -> 2.22
- resolvconf: update 1.87 -> 1.91
- rng-tools: upgrade 6.14 -> 6.15
- rpcsvc-proto: upgrade 1.4.2 -> 1.4.3
- rpm: update 4.16.1.3 -> 4.17.0
- rt-tests: update 2.1 -> 2.3
- ruby: update 3.0.2 -> 3.1.1
- rust: update 1.54.0 -> 1.59.0
- rxvt-unicode: upgrade 9.26 -> 9.30
- screen: upgrade 4.8.0 -> 4.9.0
- shaderc: update 2021.1 -> 2022.1
- shadow: upgrade 4.9 -> 4.11.1
- socat: upgrade 1.7.4.1 -> 1.7.4.3
- spirv-headers: bump to b42ba6 revision
- spirv-tools: update 2021.2 -> 2022.1
- sqlite3: upgrade 3.36.0 -> 3.38.2
- strace: update 5.14 -> 5.16

- stress-ng: upgrade 0.13.00 -> 0.13.12
- sudo: update 1.9.7p2 -> 1.9.10
- sysklogd: upgrade 2.2.3 -> 2.3.0
- sysstat: upgrade 12.4.3 -> 12.4.5
- systemd: update 249.3 -> 250.4
- systemtap: upgrade 4.5 -> 4.6
- sysvinit: upgrade 2.99 -> 3.01
- tzdata: update to 2022a
- u-boot: upgrade 2021.07 -> 2022.01
- uninative: Upgrade to 3.6 with gcc 12 support
- util-linux: update 2.37.2 -> 2.37.4
- vala: upgrade 0.52.5 -> 0.56.0
- valgrind: update 3.17.0 -> 3.18.1
- vim: upgrade to 8.2 patch 4681
- vte: upgrade 0.64.2 -> 0.66.2
- vulkan-headers: upgrade 1.2.182 -> 1.2.191
- vulkan-loader: upgrade 1.2.182 -> 1.2.198.1
- vulkan-samples: update to latest revision
- vulkan-tools: upgrade 1.2.182 -> 1.2.191
- vulkan: update 1.2.191.0 -> 1.3.204.1
- waffle: update 1.6.1 -> 1.7.0
- wayland-protocols: upgrade 1.21 -> 1.25
- wayland: upgrade 1.19.0 -> 1.20.0
- webkitgtk: upgrade 2.34.0 -> 2.36.0
- weston: upgrade 9.0.0 -> 10.0.0
- wget: update 1.21.1 -> 1.21.3
- wireless-regdb: upgrade 2021.07.14 -> 2022.02.18
- wpa-supPLICant: update 2.9 -> 2.10
- wpebackend-fdo: upgrade 1.10.0 -> 1.12.0
- xauth: upgrade 1.1 -> 1.1.1
- xf86-input-libinput: update to 1.2.1
- xf86-video-intel: update to latest commit



- xkeyboard-config: update to 2.35.1
- xorgproto: update to 2021.5
- xserver-xorg: update 1.20.13 -> 21.1.3
- xwayland: update 21.1.2 -> 22.1.0
- xxhash: upgrade 0.8.0 -> 0.8.1
- zstd: update 1.5.0 -> 1.5.2

## Contributors to 4.0

Thanks to the following people who contributed to this release:

- Abongwa Amahnui Bonalais
- Adriaan Schmidt
- Adrian Freihofer
- Ahmad Fatoum
- Ahmed Hossam
- Ahsan Hussain
- Alejandro Hernandez Samaniego
- Alessio Igor Bogani
- Alexander Kanavin
- Alexandre Belloni
- Alexandru Ardelean
- Alexey Brodtkin
- Alex Stewart
- Andreas Müller
- Andrei Gherzan
- Andrej Valek
- Andres Beltran
- Andrew Jeffery
- Andrey Zhizhikin
- Anton Mikanovich
- Anuj Mittal
- Bill Pittman
- Bruce Ashfield
- Caner Altinbasak

- Carlos Rafael Giani
- Chaitanya Vadrevu
- Changhyeok Bae
- Changqing Li
- Chen Qi
- Christian Eggers
- Claudius Heine
- Claus Stovgaard
- Daiane Angolini
- Daniel Ammann
- Daniel Gomez
- Daniel McGregor
- Daniel Müller
- Daniel Wagenknecht
- David Joyner
- David Reyna
- Denys Dmytriyenko
- Dhruva Gole
- Diego Sueiro
- Dmitry Baryshkov
- Ferry Toth
- Florian Amstutz
- Henry Kleynhans
- He Zhe
- Hongxu Jia
- Hsia-Jun(Randy) Li
- Ian Ray
- Jacob Kroon
- Jagadeesh Krishnanjanappa
- Jasper Orschulko
- Jim Wilson
- Joel Winarske

- Joe Slater
- Jon Mason
- Jose Quaresma
- Joshua Watt
- Justin Bronder
- Kai Kang
- Kamil Dziezyk
- Kevin Hao
- Khairul Rohaizzat Jamaluddin
- Khem Raj
- Kiran Surendran
- Konrad Weihmann
- Kory Maincent
- Lee Chee Yang
- Leif Middelschulte
- Lei Maohui
- Li Wang
- Liwei Song
- Luca Boccassi
- Lukasz Majewski
- Luna Gräfe
- Manuel Leonhardt
- Marek Vasut
- Mark Hatle
- Markus Niebel
- Markus Volk
- Marta Rybczynska
- Martin Beeger
- Martin Jansa
- Matthias Klein
- Matt Madison
- Maximilian Blenk

- Max Krummenacher
- Michael Halstead
- Michael Olbrich
- Michael Opdenacker
- Mike Crowe
- Ming Liu
- Mingli Yu
- Minjae Kim
- Nicholas Sielicki
- Olaf Mandel
- Oleh Matiussha
- Oleksandr Kravchuk
- Oleksandr Ocheretnyi
- Oleksandr Suvorov
- Oleksiy Obitotskyy
- Otavio Salvador
- Pablo Saavedra
- Paul Barker
- Paul Eggleton
- Pavel Zhukov
- Peter Hoyes
- Peter Kjellerstedt
- Petr Vorel
- Pgowda
- Quentin Schulz
- Ralph Siemsen
- Randy Li
- Randy MacLeod
- Rasmus Villemoes
- Ricardo Salveti
- Richard Neill
- Richard Purdie

- Robert Joslyn
- Robert P. J. Day
- Robert Yang
- Ross Burton
- Rudolf J Streif
- Sakib Sajal
- Samuli Piippo
- Saul Wold
- Scott Murray
- Sean Anderson
- Simone Weiss
- Simon Kuhnle
- S. Lockwood-Childs
- Stefan Herbrechtsmeier
- Steve Sakoman
- Sundeep KOKKONDA
- Tamizharasan Kumar
- Tean Cunningham
- Teoh Jay Shen
- Thomas Perrot
- Tim Orling
- Tobias Kaufmann
- Tom Hochstein
- Tony McDowell
- Trevor Gamblin
- Ulrich Ölmann
- Valerii Chernous
- Vivien Didelot
- Vyacheslav Yurkov
- Wang Mingyu
- Xavier Berger
- Yi Zhao

- Yongxin Liu
- Yureka
- Zev Weiss
- Zheng Ruoqin
- Zoltán Böszörményi
- Zygmunt Krynicki

## Repositories / Downloads for 4.0

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0`
- Git Revision: `00cfdde791a0176c134f31e5a09eff725e75b905`
- Release Artefact: `poky-00cfdde791a0176c134f31e5a09eff725e75b905`
- sha: `4cedb491b7bf0d015768c61690f30d7d73f4266252d6fba907bba97eac83648c`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0/poky-00cfdde791a0176c134f31e5a09eff725e75b905.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0/poky-00cfdde791a0176c134f31e5a09eff725e75b905.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0`
- Git Revision: `92fcb6570bddd0c5717d8cfd38ecf3e44942b0f`
- Release Artefact: `oecore-92fcb6570bddd0c5717d8cfd38ecf3e44942b0f`
- sha: `c042629752543a10b0384b2076b1ee8742fa5e8112aef7b00b3621f8387a51c6`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0/oecore-92fcb6570bddd0c5717d8cfd38ecf3e44942b0f.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0/oecore-92fcb6570bddd0c5717d8cfd38ecf3e44942b0f.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`

- sha: 49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0
- Git Revision: c212b0f3b542efa19f15782421196b7f4b64b0b9
- Release Artefact: bitbake-c212b0f3b542efa19f15782421196b7f4b64b0b9
- sha: 6872095c7d7be5d791ef3e18b6bab2d1e0e237962f003d2b00dc7bd6fb6d2ef7
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0/bitbake-c212b0f3b542efa19f15782421196b7f4b64b0b9.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0/bitbake-c212b0f3b542efa19f15782421196b7f4b64b0b9.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0
- Git Revision: a6f571ad5b087385cad8765ed455c4b4eaeebca6

### 17.11.3 Release notes for 4.0.1 (kirkstone)

#### Security Fixes in 4.0.1

- linux-yocto/5.15: fix CVE-2022-28796
- python3: ignore CVE-2015-20107

- e2fsprogs: fix [CVE-2022-1304](#)
- lua: fix [CVE-2022-28805](#)
- busybox: fix [CVE-2022-28391](#)

### Fixes in 4.0.1

- abi\_version/ssstate: Bump hashequiv and sstate versions due to git changes
- apt: add apt selftest to test signed package feeds
- apt: upgrade 2.4.4 -> 2.4.5
- arch-armv8-2a.inc: fix a typo in TUNEVALID variable
- babeltrace: Disable warnings as errors
- base: Avoid circular references to our own scripts
- base: Drop git intercept
- build-appliance-image: Update to kirkstone head revision
- build-appliance: Switch to kirkstone branch
- buildtools-tarball: Only add cert envvars if certs are included
- busybox: Use base\_bindir instead of hardcoding /bin path
- cases/buildepox.py: fix typo
- create-spdx: delete virtual/kernel dependency to fix FreeRTOS build
- create-spdx: fix error when symlink cannot be created
- cve-check: add JSON format to summary output
- cve-check: fix symlinks where link and output path are equal
- cve-check: no need to depend on the fetch task
- cve-update-db-native: let the user to drive the update interval
- cve-update-db-native: update the CVE database once a day only
- cve\_check: skip remote patches that haven't been fetched when searching for CVE tags
- dev-manual: add command used to add the signed-off-by line.
- devshell.bbclass: Allow devshell & pydevshell to use the network
- docs: conf.py: fix cve extlinks caption for sphinx <4.0
- docs: migration-guides: migration-3.4: mention that hardcoded password are supported if hashed
- docs: migration-guides: release-notes-4.0: fix risc-v typo
- docs: migration-guides: release-notes-4.0: replace kernel placeholder with correct recipe name
- docs: ref-manual: variables: add hashed password example in [EXTRA\\_USERS\\_PARAMS](#)
- docs: set\_versions.py: add information about obsolescence of a release



- docs: set\_versions.py: fix latest release of a branch being shown twice in switchers.js
- docs: set\_versions.py: fix latest version of an active release shown as obsolete
- docs: set\_versions.py: mark as obsolete only branches and old tags from obsolete releases
- docs: sphinx-static: switchers.js.in: do not mark branches as outdated
- docs: sphinx-static: switchers.js.in: fix broken switcher for branches
- docs: sphinx-static: switchers.js.in: improve obsolete version detection
- docs: sphinx-static: switchers.js.in: remove duplicate for outdated versions
- docs: sphinx-static: switchers.js.in: rename all\_versions to switcher\_versions
- docs: update Bitbake objects.inv location for master branch
- documentation/brief-yoctoprojectqs: add directory for local.conf
- gcompat: Fix build when usrmerge distro feature is enabled
- git: correct license
- git: upgrade 2.35.2 -> 2.35.3
- glib: upgrade 2.72.0 -> 2.72.1
- glibc: ptest: Fix glibc-tests package issue
- gnupg: Disable FORTIFY\_SOURCES on mips
- go.bbclass: disable the use of the default configuration file
- gstreamer1.0-plugins-bad: drop patch
- gstreamer1.0-plugins-good: Fix libsoup dependency
- gstreamer1.0: Minor documentation addition
- install/devshell: Introduce git intercept script due to fakeroot issues
- kernel-yocto.bbclass: Fixup do\_kernel\_configcheck usage of KMETA
- libc-glibc: Use libxcrypt to provide virtual/crypt
- libgit2: upgrade 1.4.2 -> 1.4.3
- libsoup: upgrade 3.0.5 -> 3.0.6
- libusb1: upgrade 1.0.25 -> 1.0.26
- linux-firmware: correct license for ar3k firmware
- linux-firmware: upgrade 20220310 -> 20220411
- linux-yocto/5.10: base: enable kernel crypto userspace API
- linux-yocto/5.10: update to v5.10.112
- linux-yocto/5.15: arm: poky-tiny cleanup and fixes
- linux-yocto/5.15: base: enable kernel crypto userspace API

- linux-yocto/5.15: fix -standard kernel build issue
- linux-yocto/5.15: fix ppc boot
- linux-yocto/5.15: fix qemuarm graphical boot
- linux-yocto/5.15: kasan: fix BUG: sleeping function called from invalid context
- linux-yocto/5.15: netfilter: conntrack: avoid useless indirection during conntrack destruction
- linux-yocto/5.15: update to v5.15.36
- linux-yocto: enable powerpc-debug fragment
- mdadm: Drop clang specific cflags
- migration-3.4: add missing entry on [EXTRA\\_USERS\\_PARAMS](#)
- migration-guides: add release notes for 4.0
- migration-guides: complete migration guide for 4.0
- migration-guides: release-notes-4.0: mention [LTS](#) release
- migration-guides: release-notes-4.0: update 'Repositories / Downloads' section
- migration-guides: stop including documents with ".. include"
- musl: Fix build when usrmerge distro feature is enabled
- ncurses: use COPYING file
- neard: Switch [SRC\\_URI](#) to git repo
- oeqa/selftest: add test for git working correctly inside pseudo
- openssl: minor security upgrade 3.0.2 -> 3.0.3
- package.bbclass: Prevent perform\_packagecopy from removing /sysroot-only
- package: Ensure we track whether PRSERV was active or not
- package\_manager: fix missing dependency on gnupg when signing deb package feeds
- poky-tiny: enable qemuarmv5/qemuarm64 and cleanups
- poky.conf: bump version for 4.0.1 release
- qemu.bbclass: Extend ppc/ppc64 extra options
- qemuarm64: use virtio pci interfaces
- qemuarmv5: use arm-versatile-926ejs [KMACHINE](#)
- ref-manual: Add [XZ\\_THREADS](#) and [XZ\\_MEMLIMIT](#)
- ref-manual: add [KERNEL\\_DEBUG\\_TIMESTAMPS](#)
- ref-manual: add [ZSTD\\_THREADS](#)
- ref-manual: add a note about hard-coded passwords
- ref-manual: add empty-dirs QA check and QA\_EMPTY\_DIRS\*

- ref-manual: add mention of vendor filtering to *CVE\_PRODUCT*
- ref-manual: mention wildcarding support in *INCOMPATIBLE\_LICENSE*
- releases: update for yocto 4.0
- rootfs-postcommands: fix symlinks where link and output path are equal
- ruby: upgrade 3.1.1 -> 3.1.2
- sanity: skip make 4.2.1 warning for debian
- scripts/git: Ensure we don't have circular references
- scripts: Make git intercept global
- seatd: Disable overflow warning as error on ppc64/musl
- selftest/lic\_checksum: Add test for filename containing space
- set\_versions: update for 4.0 release
- staging: Ensure we filter out ourselves
- strace: fix ptest failure in landlock
- subversion: upgrade to 1.14.2
- systemd-boot: remove outdated EFI\_LD comment
- systemtap: Fix build with gcc-12
- terminal.py: Restore error output from Terminal
- u-boot: Correct the *SRC\_URI*
- u-boot: Inherit pkgconfig
- update\_udev\_hwdb: fix multilib issue with systemd
- util-linux: Create u-a symlink for findfs utility
- virgl: skip headless test on alma 8.6
- webkitgtk: adjust patch status
- wic: do not use PARTLABEL for msdos partition tables
- wireless-regdb: upgrade 2022.02.18 -> 2022.04.08
- xserver-xorg: Fix build with gcc12
- yocto-bsps: update to v5.15.36

### Contributors to 4.0.1

- Abongwa Amahnui Bonalais
- Alexander Kanavin
- Bruce Ashfield
- Carlos Rafael Giani

- Chen Qi
- Davide Gardenal
- Dmitry Baryshkov
- Ferry Toth
- Henning Schild
- Jon Mason
- Justin Bronder
- Kai Kang
- Khem Raj
- Konrad Weihmann
- Lee Chee Yang
- Marta Rybczynska
- Martin Jansa
- Matt Madison
- Michael Halstead
- Michael Opdenacker
- Naveen Saini
- Nicolas Dechesne
- Paul Eggleton
- Paul Gortmaker
- Paulo Neves
- Peter Kjellerstedt
- Peter Marko
- Pgowda
- Portia
- Quentin Schulz
- Rahul Kumar
- Richard Purdie
- Robert Joslyn
- Robert Yang
- Roland Hieber
- Ross Burton

- Russ Dill
- Steve Sakoman
- Wang Mingyu
- Zheng Ruoqin

## Repositories / Downloads for 4.0.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.1`
- Git Revision: `8c489602f218bcf21de0d3c9f8cf620ea5f06430`
- Release Artefact: `poky-8c489602f218bcf21de0d3c9f8cf620ea5f06430`
- sha: `65c545a316bd8efb13ae1358ecccc8953543be908008103b51f7f90aed960d00`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.1/poky-8c489602f218bcf21de0d3c9f8cf620ea5f06430.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.1/poky-8c489602f218bcf21de0d3c9f8cf620ea5f06430.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.1`
- Git Revision: `cb8647c08959abb1d6b7c2b3a34b4b415f66d7ee`
- Release Artefact: `oecore-cb8647c08959abb1d6b7c2b3a34b4b415f66d7ee`
- sha: `43981b8fad82f601618a133dffbec839524f0d0a055efc3d8f808cbfd811ab17`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.1/oecore-cb8647c08959abb1d6b7c2b3a34b4b415f66d7ee.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.1/oecore-cb8647c08959abb1d6b7c2b3a34b4b415f66d7ee.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.1`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.1/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.1/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.1
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.1/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.1/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0
- Git Revision: 59c16ae6c55c607c56efd2287537a1b97ba2bf52
- Release Artefact: bitbake-59c16ae6c55c607c56efd2287537a1b97ba2bf52
- sha: 3ae466c31f738fc45c3d7c6f665952d59f01697f2667ea42f0544d4298dd6ef0
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.1/bitbake-59c16ae6c55c607c56efd2287537a1b97ba2bf52.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.1/bitbake-59c16ae6c55c607c56efd2287537a1b97ba2bf52.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.1
- Git Revision: 4ec9df3336a425719a9a35532504731ce56984ca

## 17.11.4 Release notes for Yocto-4.0.2 (Kirkstone)

### Security Fixes in Yocto-4.0.2

- libxslt: Mark CVE-2022-29824 as not applying
- tiff: Add jbig *PACKAGECONFIG* and clarify IGNORE CVE-2022-1210
- tiff: mark CVE-2022-1622 and CVE-2022-1623 as invalid

- pcre2:fix [CVE-2022-1586](#) Out-of-bounds read
- curl: fix [CVE-2022-22576](#), [CVE-2022-27775](#), [CVE-2022-27776](#), [CVE-2022-27774](#), [CVE-2022-30115](#), [CVE-2022-27780](#), [CVE-2022-27781](#), [CVE-2022-27779](#) and [CVE-2022-27782](#)
- qemu: fix [CVE-2021-4206](#) and [CVE-2021-4207](#)
- freetype: fix [CVE-2022-27404](#), [CVE-2022-27405](#) and [CVE-2022-27406](#)

### Fixes in Yocto-4.0.2

- alsa-plugins: fix libavtp vs. avtp packageconfig
- archiver: don't use machine variables in shared recipes
- archiver: use bb.note instead of echo
- baremetal-image: fix broken symlink in do\_rootfs
- base-passwd: Disable shell for default users
- bash: submit patch upstream
- bind: upgrade 9.18.1 -> 9.18.2
- binutils: Bump to latest 2.38 release branch
- bitbake.conf: Make *TCLIBC* and *TCMODE* lazy assigned
- bitbake: build: Add clean\_stamp API function to allow removal of task stamps
- bitbake: data: Do not depend on vardepvalueexclude flag
- bitbake: fetch2/osc: Small fixes for osc fetcher
- bitbake: server/process: Fix logging issues where only the first message was displayed
- build-appliance-image: Update to kirkstone head revision
- buildhistory.bbclass: fix shell syntax when using dash
- cairo: Add missing GPLv3 license checksum entry
- classes: rootfs-postcommands: add skip option to overlayfs\_qa\_check
- cronie: upgrade 1.6.0 -> 1.6.1
- cups: upgrade 2.4.1 -> 2.4.2
- cve-check.bbclass: Added do\_populate\_sdk[recrdeptask].
- cve-check: Add helper for symlink handling
- cve-check: Allow warnings to be disabled
- cve-check: Fix report generation
- cve-check: Only include installed packages for rootfs manifest
- cve-check: add support for Ignored CVEs
- cve-check: fix return type in check\_cves

- cve-check: move update\_symlinks to a library
- cve-check: write empty fragment files in the text mode
- cve-extra-exclusions: Add kernel CVEs
- cve-update-db-native: make it possible to disable database updates
- devtool: Fix \_copy\_file() TypeError
- e2fsprogs: add alternatives handling of lsattr as well
- e2fsprogs: update upstream status
- efivar: add musl libc compatibility
- epiphany: upgrade 42.0 -> 42.2
- ffmpeg: upgrade 5.0 -> 5.0.1
- fribidi: upgrade 1.0.11 -> 1.0.12
- gcc-cross-canadian: Add nativesdk-zstd dependency
- gcc-source: Fix incorrect task dependencies from \${B}
- gcc: Upgrade to 11.3 release
- gcc: depend on zstd-native
- git: fix override syntax in *RDEPENDS*
- glib-2.0: upgrade 2.72.1 -> 2.72.2
- glibc: Drop make-native dependency
- go: upgrade 1.17.8 -> 1.17.10
- gst-devtools: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-libav: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-omx: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-plugins-bad: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-plugins-base: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-plugins-good: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-plugins-ugly: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-python: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-rtsp-server: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0-vaapi: upgrade 1.20.1 -> 1.20.2
- gstreamer1.0: upgrade 1.20.1 -> 1.20.2
- gtk+3: upgrade 3.24.33 -> 3.24.34
- gtk-doc: Fix potential shebang overflow on gtkdoc-mkhtml2



- image.bbclass: allow overriding dependency on virtual/kernel:do\_deploy
- insane.bbclass: make sure to close .patch files
- iso-codes: upgrade 4.9.0 -> 4.10.0
- kernel-yocto.bbclass: Reset to exiting on non-zero return code at end of task
- libcgroup: upgrade 2.0.1 -> 2.0.2
- liberror-perl: Update sstate/equiv versions to clean cache
- libinput: upgrade 1.19.3 -> 1.19.4
- libpcrc2: upgrade 10.39 -> 10.40
- librepo: upgrade 1.14.2 -> 1.14.3
- libseccomp: Add missing files for ptests
- libseccomp: Correct *LIC\_FILES\_CHKSUM*
- libxkbcommon: upgrade 1.4.0 -> 1.4.1
- libxml2: Upgrade 2.9.13 -> 2.9.14
- license.bbclass: Bound beginline and endline in copy\_license\_files()
- license\_image.bbclass: Make QA errors fail the build
- linux-firmware: add support for building snapshots
- linux-firmware: package new Qualcomm firmware
- linux-firmware: replace mkdir by install
- linux-firmware: split ath3k firmware
- linux-firmware: upgrade to 20220610
- linux-yocto/5.10: update to v5.10.119
- linux-yocto/5.15: Enable MDIO bus config
- linux-yocto/5.15: bpf: explicitly disable unpriv eBPF by default
- linux-yocto/5.15: cfg/xen: Move x86 configs to separate file
- linux-yocto/5.15: update to v5.15.44
- local.conf.sample: Update sstate url to new 'all' path
- logrotate: upgrade 3.19.0 -> 3.20.1
- lttnng-modules: Fix build failure for 5.10.119+ and 5.15.44+ kernel
- lttnng-modules: fix build against 5.18-rc7+
- lttnng-modules: fix shell syntax
- lttnng-ust: upgrade 2.13.2 -> 2.13.3
- lzo: Add further info to a patch and mark as Inactive-Upstream

- madevs: Don't use COPYING.patch just to add license file into \${S}
- manuals: switch to the sstate mirror shared between all versions
- mesa.inc: package 00-radv-defaults.conf
- mesa: backport a patch to support compositors without zwp\_linux\_dmabuf\_v1 again
- mesa: upgrade to 22.0.3
- meson.bbclass: add cython binary to cross/native toolchain config
- mmc-utils: upgrade to latest revision
- mobile-broadband-provider-info: upgrade 20220315 -> 20220511
- ncurses: update to patchlevel 20220423
- oeqa/selftest/cve\_check: add tests for Ignored and partial reports
- oeqa/selftest/cve\_check: add tests for recipe and image reports
- oescripts: change compare logic in OEListPackageconfigTests
- openssl: Backport fix for ptest cert expiry
- overlayfs: add docs about skipping QA check & service dependencies
- ovmf: Fix native build with gcc-12
- patch.py: make sure that patches/series file exists before quilt pop
- pciutils: avoid lspci conflict with busybox
- perl: Add dependency on make-native to avoid race issues
- perl: Fix build with gcc-12
- poky.conf: bump version for 4.0.2
- popt: fix override syntax in *RDEPENDS*
- pypi.bbclass: Set *CVE\_PRODUCT* to *PYPI\_PACKAGE*
- python3: Ensure stale empty python module directories don't break the build
- python3: Remove problematic paths from sysroot files
- python3: fix reproducibility issue with python3-core
- python3: use built-in distutils for ptest, rather than setuptools' 'fork'
- python: Avoid shebang overflow on python-config.py
- rootfs-postcommands.bbclass: correct comments
- rootfs.py: close kernel\_abi\_ver\_file
- rootfs.py: find .ko.zst kernel modules
- rust-common: Drop LLVM\_TARGET and simplify
- rust-common: Ensure sstate signatures have correct dependencies for do\_rust\_gen\_targets

- rust-common: Fix for target definitions returning 'NoneType' for arm
- rust-common: Fix native signature dependency issues
- rust-common: Fix sstate signatures between arm hf and non-hf
- sanity: Don't warn about make 4.2.1 for mint
- sanity: Switch to make 4.0 as a minimum version
- sed: Specify shell for "nobody" user in run-ptest
- selftest/imagefeatures/overlays: Always append to *DISTRO\_FEATURES*
- selftest/multiconfig: Test that multiconfigs in separate layers works
- sqlite3: upgrade to 3.38.5
- staging.bbclass: process direct dependencies in deterministic order
- staging: Fix rare sysroot corruption issue
- strace: Don't run ptest as "nobody"
- systemd: Correct 0001-pass-correct-parameters-to-getdents64.patch
- systemd: Correct path returned in sd\_path\_lookup()
- systemd: Document future actions needed for set of musl patches
- systemd: Drop 0001-test-parse-argument-Include-signal.h.patch
- systemd: Drop 0002-don-t-use-glibc-specific-qsort\_r.patch
- systemd: Drop 0016-Hide-\_\_start\_BUS\_ERROR\_MAP-and-\_\_stop\_BUS\_ERROR\_MAP.patch
- systemd: Drop redundant musl patches
- systemd: Fix build regression with latest update
- systemd: Remove \_\_compare\_fn\_t type in musl-specific patch
- systemd: Update patch status
- systemd: systemd-systemctl: Support instance conf files during enable
- systemd: update 0008-add-missing-FTW\_macros-for-musl.patch
- systemd: upgrade 250.4 -> 250.5
- uboot-sign: Fix potential index error issues
- valgrind: submit arm patches upstream
- vim: Upgrade to 8.2.5083
- webkitgtk: upgrade to 2.36.3
- wic/plugins/rootfs: Fix permissions when splitting rootfs folders across partitions
- xwayland: upgrade 22.1.0 -> 22.1.1
- xxhash: fix build with gcc 12

- zip/unzip: mark all submittable patches as Inactive-Upstream

### **Known Issues in Yocto-4.0.2**

- There were build failures at the autobuilder due to a known scp issue on Fedora-36 hosts.

### **Contributors to Yocto-4.0.2**

- Alex Kiernan
- Alexander Kanavin
- Aryaman Gupta
- Bruce Ashfield
- Claudius Heine
- Davide Gardenal
- Dmitry Baryshkov
- Ernst Sjöstrand
- Felix Moessbauer
- Gunjan Gupta
- He Zhe
- Hitendra Prajapati
- Jack Mitchell
- Jeremy Puhlmán
- Jiaqing Zhao
- Joerg Vehlowl
- Jose Quaresma
- Kai Kang
- Khem Raj
- Konrad Weihmann
- Marcel Ziswiler
- Markus Volk
- Marta Rybczynska
- Martin Jansa
- Michael Opdenacker
- Mingli Yu
- Naveen Saini
- Nick Potenski

- Paulo Neves
- Pavel Zhukov
- Peter Kjellerstedt
- Rasmus Villemoes
- Richard Purdie
- Robert Joslyn
- Ross Burton
- Samuli Piippo
- Sean Anderson
- Stefan Wiehler
- Steve Sakoman
- Sundeep Kokkonda
- Tomasz Dziendzielski
- Xiaobing Luo
- Yi Zhao
- leimaohui
- Wang Mingyu

## Repositories / Downloads for Yocto-4.0.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.2](#)
- Git Revision: [a5ea426b1da472fc8549459fff3c1b8c6e02f4b5](#)
- Release Artefact: [poky-a5ea426b1da472fc8549459fff3c1b8c6e02f4b5](#)
- sha: [474ddfaced6661be054c161597a1a5273188dfe021b31d6156955d93c6b7359](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.2/poky-a5ea426b1da472fc8549459fff3c1b8c6e02f4b5.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.2/poky-a5ea426b1da472fc8549459fff3c1b8c6e02f4b5.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.2](#)
- Git Revision: [eea52e0c3d24c79464f4afdbc3c397e1cb982231](#)

- Release Artefact: oecore-eea52e0c3d24c79464f4afdbc3c397e1cb982231
- sha: 252d5c2c2db7e14e7365fcc69d32075720b37d629894bae36305eba047a39907
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.2/oecore-eea52e0c3d24c79464f4afdbc3c397e1cb982231.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.2/oecore-eea52e0c3d24c79464f4afdbc3c397e1cb982231.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.2
- Git Revision: a90614a6498c3345704e9611f2842eb933dc51c1
- Release Artefact: meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1
- sha: 49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.2/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.2/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.2
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.2/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.2/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.2
- Git Revision: b8fd6f5d9959d27176ea016c249cf6d35ac8ba03
- Release Artefact: bitbake-b8fd6f5d9959d27176ea016c249cf6d35ac8ba03
- sha: 373818b1dee2c502264edf654d6d8f857b558865437f080e02d5ba6bb9e72cc3
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.2/bitbake-b8fd6f5d9959d27176ea016c249cf6d35ac8ba03.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.2/bitbake-b8fd6f5d9959d27176ea016c249cf6d35ac8ba03.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.2`
- Git Revision: `662294dccd028828d5c7e9fd8f5c8e14df53df4b`

### 17.11.5 Release notes for Yocto-4.0.3 (Kirkstone)

#### Security Fixes in Yocto-4.0.3

- binutils: fix CVE-2019-1010204
- busybox: fix CVE-2022-30065
- cups: ignore CVE-2022-26691
- curl: Fix CVE-2022-32205, CVE-2022-32206, CVE-2022-32207 and CVE-2022-32208
- dpkg: fix CVE-2022-1664
- ghostscript: fix CVE-2022-2085
- harfbuzz: fix CVE-2022-33068
- libtirpc: fix CVE-2021-46828
- lua: fix CVE-2022-33099
- nasm: ignore CVE-2020-18974
- qemu: fix CVE-2022-35414
- qemu: ignore CVE-2021-20255 and CVE-2019-12067
- tiff: fix CVE-2022-1354, CVE-2022-1355, CVE-2022-2056, CVE-2022-2057 and CVE-2022-2058
- u-boot: fix CVE-2022-34835
- unzip: fix CVE-2022-0529 and CVE-2022-0530

#### Fixes in Yocto-4.0.3

- alsa-state: correct license
- at: take tarballs from debian
- base.bbclass: Correct the test for obsolete license exceptions
- base/reproducible: Change Source Date Epoch generation methods
- bin\_package: install into base\_prefix
- bind: Remove legacy python3 `PACKAGECONFIG` code
- bind: upgrade to 9.18.4
- binutils: stable 2.38 branch updates

- build-appliance-image: Update to kirkstone head revision
- cargo\_common.bbclass: enable bitbake vendoring for externalsrc
- coreutils: Tweak packaging variable names for coreutils-dev
- curl: backport openssl fix CN check error code
- cve-check: hook cleanup to the BuildCompleted event, not CookerExit
- cve-extra-exclusions: Clean up and ignore three CVEs (2xqemu and nasm)
- devtool: finish: handle patching when *S* points to subdir of a git repo
- devtool: ignore pn- overrides when determining *SRC\_URI* overrides
- docs: BB\_HASHSERVE\_UPSTREAM: update to new host
- dropbear: break dependency on base package for -dev package
- efivar: fix import functionality
- encodings: update to 1.0.6
- epiphany: upgrade to 42.3
- externalsrc.bbclass: support crate fetcher on externalsrc
- font-util: update 1.3.2 -> 1.3.3
- gcc-runtime: Fix build when using gold
- gcc-runtime: Fix missing *MLPREFIX* in debug mappings
- gcc-runtime: Pass -nostartfiles when building dummy libstdc++.so
- gcc: Backport a fix for gcc bug 105039
- git: upgrade to v2.35.4
- glib-2.0: upgrade to 2.72.3
- glib-networking: upgrade to 2.72.1
- glibc : stable 2.35 branch updates
- glibc-tests: Avoid reproducibility issues
- glibc-tests: not clear *BBCLASSEXTEND*
- glibc: revert one upstream change to work around broken *DEBUG\_BUILD* build
- glibc: stable 2.35 branch updates
- gnupg: upgrade to 2.3.7
- go: upgrade to v1.17.12
- gobject-introspection-data: Disable cache for g-ir-scanner
- gperf: Add a patch to work around reproducibility issues
- gperf: Switch to upstream patch



- `gst-devtools`: upgrade to 1.20.3
- `gststreamer1.0-libav`: upgrade to 1.20.3
- `gststreamer1.0-omx`: upgrade to 1.20.3
- `gststreamer1.0-plugins-bad`: upgrade to 1.20.3
- `gststreamer1.0-plugins-base`: upgrade to 1.20.3
- `gststreamer1.0-plugins-good`: upgrade to 1.20.3
- `gststreamer1.0-plugins-ugly`: upgrade to 1.20.3
- `gststreamer1.0-python`: upgrade to 1.20.3
- `gststreamer1.0-rtsp-server`: upgrade to 1.20.3
- `gststreamer1.0-vaapi`: upgrade to 1.20.3
- `gststreamer1.0`: upgrade to 1.20.3
- `gtk-doc`: Remove hardcoded buildpath
- `harfbuzz`: Fix compilation with clang
- `initramfs-framework`: move storage mounts to actual rootfs
- `initscripts`: run `umountnfs` as a KILL script
- `insane.bbclass`: `host-user-contaminated`: Correct per package home path
- `insane`: Fix buildpaths test to work with special devices
- `kernel-arch`: Fix buildpaths leaking into external module compiles
- `kernel-devsrc`: fix reproducibility and buildpaths QA warning
- `kernel-devsrc`: `ppc32`: fix reproducibility
- `kernel-uboot.bbclass`: Use `vmlinux.initramfs` when `INITRAMFS_IMAGE_BUNDLE` set
- `kernel.bbclass`: pass `LD` also in `savedefconfig`
- `libffi`: fix native build being not portable
- `libgcc`: Fix standalone target builds with `usrmerge` distro feature
- `libmodule-build-perl`: Use `env` utility to find perl interpreter
- `libsoup`: upgrade to 3.0.7
- `libuv`: upgrade to 1.44.2
- `linux-firmware`: upgrade to 20220708
- `linux-firmware`: restore `WHENCE_CHKSUM` variable
- `linux-yocto-rt/5.15`: update to `-rt48` (and fix `-stable` merge)
- `linux-yocto/5.10`: fix `build_OID_registry/conmakehash` buildpaths warning
- `linux-yocto/5.10`: fix buildpaths issue with `gen-mach-types`

- linux-yocto/5.10: fix buildpaths issue with pnmtologo
- linux-yocto/5.10: update to v5.10.135
- linux-yocto/5.15: drop obsolete GPIO sysfs ABI
- linux-yocto/5.15: fix build\_OID\_registry buildpaths warning
- linux-yocto/5.15: fix buildpaths issue with gen-mach-types
- linux-yocto/5.15: fix buildpaths issue with pnmtologo
- linux-yocto/5.15: fix qemuipc buildpaths warning
- linux-yocto/5.15: fix reproducibility issues
- linux-yocto/5.15: update to v5.15.59
- log4cplus: upgrade to 2.0.8
- lttnng-modules: Fix build failure for kernel v5.15.58
- lttnng-modules: upgrade to 2.13.4
- lua: Fix multilib buildpath reproducibility issues
- mkfontscale: upgrade to 1.2.2
- oe-selftest-image: Ensure the image has sftp as well as dropbear
- oe-selftest: devtool: test modify git recipe building from a subdir
- oeqa/runtime/scp: Disable scp test for dropbear
- oeqa/runtime: add test that the kernel has CONFIG\_PREEMPT\_RT enabled
- oeqa/sdk: drop the nativesdk-python 2.x test
- openssh: Add openssh-sftp-server to openssh *RDEPENDS*
- openssh: break dependency on base package for -dev package
- openssl: update to 3.0.5
- package.bbclass: Avoid stripping signed kernel modules in splitdebuginfo
- package.bbclass: Fix base directory for debugsource files when using externalsrc
- package.bbclass: Fix kernel source handling when not using externalsrc
- package\_manager/ipk: do not pipe stderr to stdout
- packagegroup-core-ssh-dropbear: Add openssh-sftp-server recommendation
- patch: handle if *S* points to a subdirectory of a git repo
- perf: fix reproducibility in 5.19+
- perf: fix reproducibility in older releases of Linux
- perf: sort-pmuevents: really keep array terminators
- perl: don't install Makefile.old into perl-ptest

- poky.conf: bump version for 4.0.3
- pulseaudio: add m4-native to *DEPENDS*
- python3: Backport patch to fix an issue in subinterpreters
- qemu: Add *PACKAGECONFIG* for brlapi
- qemu: Avoid accidental librdmacm linkage
- qemu: Avoid accidental libvdeplug linkage
- qemu: Fix slirp determinism issue
- qemu: add *PACKAGECONFIG* for capstone
- recipetool/devtool: Fix python egg whitespace issues in *PACKAGECONFIG*
- ref-manual: variables: remove sphinx directive from literal block
- rootfs-postcommands.bbclass: move host-user-contaminated.txt to \${S}
- ruby: add *PACKAGECONFIG* for capstone
- rust: fix issue building cross-canadian tools for aarch64 on x86\_64
- sanity.bbclass: Add ftps to accepted URI protocols for mirrors sanity
- selftest/runtime\_test/virgl: Disable for all almalinux
- sstatesig: Include all dependencies in SPDX task signatures
- strace: set *COMPATIBLE\_HOST* for riscv32
- systemd: Added base\_bindir into pkg\_postinst:udev-hwdb.
- udev-extraconf/initrdscripts/parted: Rename mount.blacklist -> mount.ignorelist
- udev-extraconf/mount.sh: add LABELs to mountpoints
- udev-extraconf/mount.sh: ignore lvm in automount
- udev-extraconf/mount.sh: only mount devices on hotplug
- udev-extraconf/mount.sh: save mount name in our tmp filecache
- udev-extraconf: fix some systemd automount issues
- udev-extraconf: force systemd-udevd to use shared MountFlags
- udev-extraconf: let automount base directory configurable
- udev-extraconf:mount.sh: fix a umount issue
- udev-extraconf:mount.sh: fix path mismatching issues
- vala: Fix on target wrapper buildpaths issue
- vala: upgrade to 0.56.2
- vim: upgrade to 9.0.0063
- waffle: correctly request wayland-scanner executable

- webkitgtk: upgrade to 2.36.4
- weston: upgrade to 10.0.1
- wic/plugins/rootfs: Fix NameError for 'orig\_path'
- wic: fix WicError message
- wireless-regdb: upgrade to 2022.06.06
- xdpinfo: upgrade to 1.3.3
- xev: upgrade to 1.2.5
- xf86-input-synaptics: upgrade to 1.9.2
- xmodmap: upgrade to 1.0.11
- xorg-app: Tweak handling of compression changes in *SRC\_URI*
- xserver-xorg: upgrade to 21.1.4
- xwayland: upgrade to 22.1.3
- yocto-bsps/5.10: fix buildpaths issue with gen-mach-types
- yocto-bsps/5.10: fix buildpaths issue with pnmologo
- yocto-bsps/5.15: fix buildpaths issue with gen-mach-types
- yocto-bsps/5.15: fix buildpaths issue with pnmologo
- yocto-bsps: buildpaths fixes
- yocto-bsps: update to v5.10.130
- yocto-bsps: buildpaths fixes
- yocto-bsps: update to v5.15.54

### Known Issues in Yocto-4.0.3

- N/A

### Contributors to Yocto-4.0.3

- Ahmed Hossam
- Alejandro Hernandez Samaniego
- Alex Kiernan
- Alexander Kanavin
- Bruce Ashfield
- Chanh Park
- Christoph Lauer
- David Bagonyi
- Dmitry Baryshkov

- He Zhe
- Hitendra Prajapati
- Jose Quaresma
- Joshua Watt
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Lucas Stach
- Markus Volk
- Martin Jansa
- Maxime Roussin-Bélanger
- Michael Opdenacker
- Mihai Lindner
- Ming Liu
- Mingli Yu
- Muhammad Hamza
- Naveen
- Pascal Bach
- Paul Eggleton
- Pavel Zhukov
- Peter Bergin
- Peter Kjellerstedt
- Peter Marko
- Pgowda
- Raju Kumar Pothuraju
- Richard Purdie
- Robert Joslyn
- Ross Burton
- Sakib Sajal
- Shruthi Ravichandran
- Steve Sakoman
- Sundeep Kokkonda

- Thomas Roos
- Tom Hochstein
- Wentao Zhang
- Yi Zhao
- Yue Tao
- gr embeter
- leimaohui
- Wang Mingyu

## Repositories / Downloads for Yocto-4.0.3

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.3](#)
- Git Revision: [387ab5f18b17c3af3e9e30dc58584641a70f359f](#)
- Release Artefact: [poky-387ab5f18b17c3af3e9e30dc58584641a70f359f](#)
- sha: [fe674186bdb0684313746caa9472134fc19e6f1443c274fe02c06cb1e675b404](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.3/poky-387ab5f18b17c3af3e9e30dc58584641a70f359f.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.3/poky-387ab5f18b17c3af3e9e30dc58584641a70f359f.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.3](#)
- Git Revision: [2cafa6ed5f0aa9df5a120b6353755d56c7c7800d](#)
- Release Artefact: [oecore-2cafa6ed5f0aa9df5a120b6353755d56c7c7800d](#)
- sha: [5181d3e8118c6112936637f01a07308b715e0e3d12c7eba338556747dfcabe92](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.3/oecore-2cafa6ed5f0aa9df5a120b6353755d56c7c7800d.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.3/oecore-2cafa6ed5f0aa9df5a120b6353755d56c7c7800d.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.3](#)

- Git Revision: [a90614a6498c3345704e9611f2842eb933dc51c1](#)
- Release Artefact: [meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1](#)
- sha: [49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.3/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.3/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.3](#)
- Git Revision: [d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- Release Artefact: [meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- sha: [c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.3/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.3/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.0](#)
- Tag: [yocto-4.0.3](#)
- Git Revision: [b8fd6f5d9959d27176ea016c249cf6d35ac8ba03](#)
- Release Artefact: [bitbake-b8fd6f5d9959d27176ea016c249cf6d35ac8ba03](#)
- sha: [373818b1dee2c502264edf654d6d8f857b558865437f080e02d5ba6bb9e72cc3](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.3/bitbake-b8fd6f5d9959d27176ea016c249cf6d35ac8ba03.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.3/bitbake-b8fd6f5d9959d27176ea016c249cf6d35ac8ba03.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.3](#)
- Git Revision: [d9b3dcf65ef25c06f552482aba460dd16862bf96](#)

## 17.11.6 Release notes for Yocto-4.0.4 (Kirkstone)

### Security Fixes in Yocto-4.0.4

- binutils : fix CVE-2022-38533
- curl: fix CVE-2022-35252
- sqlite: fix CVE-2022-35737
- grub2: fix CVE-2021-3695, CVE-2021-3696, CVE-2021-3697, CVE-2022-28733, CVE-2022-28734 and CVE-2022-28735
- u-boot: fix CVE-2022-30552 and CVE-2022-33967
- libxml2: Ignore CVE-2016-3709
- libtiff: fix CVE-2022-34526
- zlib: fix CVE-2022-37434
- gnutls: fix CVE-2022-2509
- u-boot: fix CVE-2022-33103
- qemu: fix CVE-2021-3507, CVE-2021-3929, CVE-2021-4158, CVE-2022-0216 and CVE-2022-0358

### Fixes in Yocto-4.0.4

- apr: Cache configure tests which use AC\_TRY\_RUN
- apr: Use correct strerror\_r implementation based on libc type
- apt: fix nativesdk-apt build failure during the second time build
- archiver.bbclass: remove unused do\_deploy\_archives[dirs]
- archiver.bbclass: some recipes that uses the kernelsrc bbclass uses the shared source
- autoconf: Fix strict prototype errors in generated tests
- autoconf: Update K & R stype functions
- bind: upgrade to 9.18.5
- bitbake.conf: set *BB\_DEFAULT\_UMASK* using *??=*
- bitbake: ConfHandler/BBHandler: Improve comment error messages and add tests
- bitbake: ConfHandler: Remove lingering close
- bitbake: bb/utils: movefile: use the logger for printing
- bitbake: bb/utils: remove: check the path again the expand python glob
- bitbake: bitbake-user-manual: Correct description of the *??=* operator
- bitbake: bitbake-user-manual: npm fetcher: improve description of *SRC\_URI* format
- bitbake: bitbake: bitbake-user-manual: hashserv can be accessed on a dedicated domain
- bitbake: bitbake: runqueue: add cpu/io pressure regulation



- bitbake: bitbake: runqueue: add memory pressure regulation
- bitbake: cooker: Drop sre\_constants usage
- bitbake: doc: bitbake-user-manual: add explicit target for crates fetcher
- bitbake: doc: bitbake-user-manual: document npm and npmsw fetchers
- bitbake: event.py: ignore exceptions from stdout and stderr operations in atexit
- bitbake: fetch2: Ensure directory exists before creating symlink
- bitbake: fetch2: git-sm: fix incorrect handling of git submodule relative urls
- bitbake: runqueue: Change pressure file warning to a note
- bitbake: runqueue: Fix unihash cache mismatch issues
- bitbake: toaster: fix kirkstone version
- bitbake: utils: Pass lock argument in fileslocked
- bluez5: upgrade to 5.65
- boost: fix install of fiber shared libraries
- cairo: Adapt the license information based on what is being built
- classes: cve-check: Get shared database lock
- cmake: remove CMAKE\_ASM\_FLAGS variable in toolchain file
- connman: Backports for security fixes
- core-image.bbclass: Exclude openssh complementary packages
- cracklib: Drop using register keyword
- cracklib: upgrade to 2.9.8
- create-spdx: Fix supplier field
- create-spdx: handle links to inaccessible locations
- create-spdx: ignore packing control files from ipk and deb
- cve-check: Don't use f-strings
- cve-check: close cursors as soon as possible
- devtool/upgrade: catch bb.fetch2.decodeurl errors
- devtool/upgrade: correctly clean up when recipe filename isn't yet known
- devtool: error out when workspace is using old override syntax
- ell: upgrade to 0.50
- epiphany: upgrade to 42.4
- externalsrc: Don't wipe out src dir when EXPORT\_FUNCTIONS is used.
- gcc-multilib-config: Fix i686 toolchain relocation issues

- gcr: Define `_GNU_SOURCE`
- gdk-pixbuf: upgrade to 2.42.9
- glib-networking: upgrade to 2.72.2
- go: upgrade to v1.17.13
- insane.bbclass: Skip patches not in oe-core by full path
- iso-codes: upgrade to 4.11.0
- kernel-fitimage.bbclass: add padding algorithm property in config nodes
- kernel-fitimage.bbclass: only package unique DTBs
- kernel: Always set `CC` and `LD` for the kernel build
- kernel: Use consistent make flags for menuconfig
- lib:npm\_registry: initial checkin
- libatomic-ops: upgrade to 7.6.14
- libcap: upgrade to 2.65
- libjpeg-turbo: upgrade to 2.1.4
- libpam: use `/run` instead of `/var/run` in systemd tmpfiles
- libtasn1: upgrade to 4.19.0
- liburcu: upgrade to 0.13.2
- libwebp: upgrade to 1.2.4
- libwpe: upgrade to 1.12.3
- libxml2: Port gentest.py to Python-3
- lighttpd: upgrade to 1.4.66
- linux-yocto/5.10: update genericx86\* machines to v5.10.135
- linux-yocto/5.10: update to v5.10.137
- linux-yocto/5.15: update genericx86\* machines to v5.15.59
- linux-yocto/5.15: update to v5.15.62
- linux-yocto: Fix `COMPATIBLE_MACHINE` regex match
- linux-yocto: prepend the value with a space when append to `KERNEL_EXTRA_ARGS`
- lttnng-modules: fix 5.19+ build
- lttnng-modules: fix build against mips and v5.19 kernel
- lttnng-modules: fix build for kernel 5.10.137
- lttnng-modules: replace mips compaction fix with upstream change
- lz4: upgrade to 1.9.4

- maintainers: update opkg maintainer
- meta: introduce *UBOOT\_MKIMAGE\_KERNEL\_TYPE*
- migration guides: add missing release notes
- mobile-broadband-provider-info: upgrade to 20220725
- nativesdk: Clear *TUNE\_FEATURES*
- npm: replace 'npm pack' call by 'tar czf'
- npm: return content of 'package.json' in 'npm\_pack'
- npm: take 'version' directly from 'package.json'
- npm: use npm\_registry to cache package
- oeqa/gotoolchain: put writable files in the Go module cache
- oeqa/gotoolchain: set CGO\_ENABLED=1
- oeqa/parselogs: add qemuarmv5 arm-charlcd masking
- oeqa/qemurunner: add run\_serial() comment
- oeqa/selftest: rename git.py to intercept.py
- oeqa: qemurunner: Report UNIX Epoch timestamp on login
- package\_rpm: Do not replace square brackets in %files
- packagegroup-self-hosted: update for strace
- parselogs: Ignore xf86OpenConsole error
- perf: Fix reproducibility issues with 5.19 onwards
- pinentry: enable \_XOPEN\_SOURCE on musl for wchar usage in curses
- poky.conf: add ubuntu-22.04 to tested distros
- poky.conf: bump version for 4.0.4
- pseudo: Update to include recent upstream minor fixes
- python3-pip: Fix *RDEPENDS* after the update
- ref-manual: add numa to machine features
- relocate\_sdk.py: ensure interpreter size error causes relocation to fail
- rootfs-postcommands.bbclass: avoid moving ssh host keys if etc is writable
- rootfs.py: dont try to list installed packages for baremetal images
- rootfspostcommands.py: Cleanup subid backup files generated by shadow-utils
- ruby: drop capstone support
- runqemu: Add missing space on default display option
- runqemu: display host uptime when starting

- sanity: add a comment to ensure CONNECTIVITY\_CHECK\_URIS is correct
- scripts/oe-setup-builddir: make it known where configurations come from
- scripts/runqemu.README: fix typos and trailing whitespaces
- selftest/wic: Tweak test case to not depend on kernel size
- shadow: Avoid nss warning/error with musl
- shadow: Enable subid support
- system-requirements.rst: Add Ubuntu 22.04 to list of supported distros
- systemd: Add 'no-dns-fallback' *PACKAGECONFIG* option
- systemd: Fix unwritable /var/lock when no sysvinit handling
- sysvinit-inittab/start\_getty: Fix respawn too fast
- tcp-wrappers: Fix implicit-function-declaration warnings
- tzdata: upgrade to 2022b
- util-linux: Remove --enable-raw from *EXTRA\_OECONF*
- vala: upgrade to 0.56.3
- vim: Upgrade to 9.0.0453
- watchdog: Include needed system header for function decls
- webkitgtk: upgrade to 2.36.5
- weston: upgrade to 10.0.2
- wic/bootimg-efi: use cross objcopy when building unified kernel image
- wic: add target tools to PATH when executing native commands
- wic: depend on cross-binutils
- wireless-regdb: upgrade to 2022.08.12
- wpebackend-fdo: upgrade to 1.12.1
- xinetd: Pass missing -D\_GNU\_SOURCE
- xz: update to 5.2.6

### Known Issues in Yocto-4.0.4

- N/A

### Contributors to Yocto-4.0.4

- Alejandro Hernandez Samaniego
- Alex Stewart
- Alexander Kanavin
- Alexandre Belloni

- Andrei Gherzan
- Anuj Mittal
- Aryaman Gupta
- Awais Belal
- Beniamin Sandu
- Bertrand Marquis
- Bruce Ashfield
- Changqing Li
- Chee Yang Lee
- Daiane Angolini
- Enrico Scholz
- Ernst Sjöstrand
- Gennaro Iorio
- Hitendra Prajapati
- Jacob Kroon
- Jon Mason
- Jose Quaresma
- Joshua Watt
- Kai Kang
- Khem Raj
- Kristian Amlie
- LUIS ENRIQUEZ
- Mark Hatle
- Martin Beeger
- Martin Jansa
- Mateusz Marciniec
- Michael Opdenacker
- Mihai Lindner
- Mikko Rapeli
- Ming Liu
- Niko Mauno
- Ola x Nilsson

- Otavio Salvador
- Paul Eggleton
- Pavel Zhukov
- Peter Bergin
- Peter Kjellerstedt
- Peter Marko
- Rajesh Dangi
- Randy MacLeod
- Rasmus Villemoes
- Richard Purdie
- Robert Joslyn
- Roland Hieber
- Ross Burton
- Sakib Sajal
- Shubham Kulkarni
- Steve Sakoman
- Ulrich Ölmann
- Yang Xu
- Yongxin Liu
- ghassaneben
- pgowda
- Wang Mingyu

## Repositories / Downloads for Yocto-4.0.4

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.4](#)
- Git Revision: [d64bef1c7d713b92a51228e5ade945835e5a94a4](#)
- Release Artefact: [poky-d64bef1c7d713b92a51228e5ade945835e5a94a4](#)
- sha: [b5e92506b31f88445755bad2f45978b747ad1a5bea66ca897370542df5f1e7db](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.4/poky-d64bef1c7d713b92a51228e5ade945835e5a94a4.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.4/poky-d64bef1c7d713b92a51228e5ade945835e5a94a4.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.4`
- Git Revision: `f7766da462905ec67bf549d46b8017be36cd5b2a`
- Release Artefact: `oecore-f7766da462905ec67bf549d46b8017be36cd5b2a`
- sha: `ce0ac011474db5e5f0bb1be3fb97f890a02e46252a719dbcac5813268e48ff16`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.4/oecore-f7766da462905ec67bf549d46b8017be36cd5b2a.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.4/oecore-f7766da462905ec67bf549d46b8017be36cd5b2a.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.4`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.4/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.4/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.4`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.4/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.4/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.4`

- Git Revision: [ac576d6fad6bba0cfea931883f25264ea83747ca](#)
- Release Artefact: [bitbake-ac576d6fad6bba0cfea931883f25264ea83747ca](#)
- sha: [526c2768874eeda61ade8c9ddb3113c90d36ef44a026d6690f02de6f3dd0ea12](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.4/bitbake-ac576d6fad6bba0cfea931883f25264ea83747ca.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.4/bitbake-ac576d6fad6bba0cfea931883f25264ea83747ca.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.4](#)
- Git Revision: [f632dad24c39778f948014029e74db3c871d9d21](#)

### 17.11.7 Release notes for Yocto-4.0.5 (Kirkstone)

#### Security Fixes in Yocto-4.0.5

- qemu: fix [CVE-2021-3750](#), [CVE-2021-3611](#) and [CVE-2022-2962](#)
- binutils : fix [CVE-2022-38126](#), [CVE-2022-38127](#) and [CVE-2022-38128](#)
- ttf: fix [CVE-2022-2867](#), [CVE-2022-2868](#) and [CVE-2022-2869](#)
- inetutils: fix [CVE-2022-39028](#)
- go: fix [CVE-2022-27664](#)

#### Fixes in Yocto-4.0.5

- Revert "gcc-cross-canadian: Add symlink to real-ld alongside other symlinks"
- bind: upgrade to 9.18.7
- binutils: stable 2.38 branch updates ([dc2474e7](#))
- bitbake: Fix npm to use https rather than http
- bitbake: asynrpc/client: Fix unix domain socket chdir race issues
- bitbake: bitbake: Add copyright headers where missing
- bitbake: git-sm: Error out if submodule refers to parent repo
- bitbake: runqueue: Drop deadlock breaking force fail
- bitbake: runqueue: Ensure deferred tasks are sorted by multiconfig
- bitbake: runqueue: Improve deadlock warning messages
- bitbake: siggen: Fix insufficient entropy in sigtask file names
- bitbake: tests/fetch: Allow handling of a [file://](#) url within a submodule
- build-appliance-image: Update to kirkstone head revision ([4a88ada](#))



- busybox: add devmem 128-bit support
- classes: files: Extend overlayfs-etc class
- coreutils: add openssl *PACKAGECONFIG*
- create-pull-request: don't switch the git remote protocol to git://
- dev-manual: fix reference to BitBake user manual
- expat: upgrade 2.4.8 -> 2.4.9
- files: overlayfs-etc: refactor preinit template
- gcc-cross-canadian: add default plugin linker
- gcc: add arm-v9 support
- git: upgrade 2.35.4 -> 2.35.5
- glibc-locale: explicitly remove empty dirs in \${libdir}
- glibc-tests: use += instead of :append
- glibc: stable 2.35 branch updates.(8d125a1f)
- go-native: switch from SRC\_URI:append to *SRC\_URI* +=
- image\_types\_wic.bbclass: fix cross binutils dependency
- kern-tools: allow 'y' or 'm' to avoid config audit warnings
- kern-tools: fix queue processing in relative *TOPDIR* configurations
- kernel-yocto: allow patch author date to be commit date
- libpng: upgrade to 1.6.38
- linux-firmware: package new Qualcomm firmware
- linux-firmware: upgrade 20220708 -> 20220913
- linux-libc-headers: switch from SRC\_URI:append to *SRC\_URI* +=
- linux-yocto-dev: add qemuarm64
- linux-yocto/5.10: update to v5.10.149
- linux-yocto/5.15: cfg: fix ACPI warnings for -tiny
- linux-yocto/5.15: update to v5.15.68
- local.conf.sample: correct the location of public hashserv
- ltp: Fix pread02 case trigger the glibc overflow detection
- lttnng-modules: Fix crash on powerpc64
- lttnng-tools: Disable on qemuriscv32
- lttnng-tools: Disable on riscv32
- migration-guides: add 4.0.4 release notes

- oeqa/runtime/dnf: fix typo
- own-mirrors: add crate
- perf: Fix for recent kernel upgrades
- poky.conf: bump version for 4.0.5
- poky.yaml.in: update version requirements
- python3-rfc3986-validator: switch from SRC\_URI:append to *SRC\_URI +=*
- python3: upgrade 3.10.4 -> 3.10.7
- qemu: Backport patches from upstream to support float128 on qemu-ppc64
- rpm: Remove -Wimplicit-function-declaration warnings
- rpm: update to 4.17.1
- rsync: update to 3.2.5
- stress-cpu: disable float128 math on powerpc64 to avoid SIGILL
- tune-neoversen2: support tune-neoversen2 base on armv9a
- tzdata: update to 2022d
- u-boot: switch from append to += in *SRC\_URI*
- uninative: Upgrade to 3.7 to work with glibc 2.36
- vim: Upgrade to 9.0.0598
- webkitgtk: Update to 2.36.7

### Known Issues in Yocto-4.0.5

- There are recent CVEs in key components such as openssl. They are not included in this release as it was built before the issues were known and fixes were available but these are now available on the kirkstone branch.

### Contributors to Yocto-4.0.5

- Adrian Freihofer
- Alexander Kanavin
- Alexandre Belloni
- Bhabu Bindu
- Bruce Ashfield
- Chen Qi
- Daniel McGregor
- Denys Dmytriienko
- Dmitry Baryshkov
- Florin Diaconescu

- He Zhe
- Joshua Watt
- Khem Raj
- Martin Jansa
- Michael Halstead
- Michael Opdenacker
- Mikko Rapeli
- Mingli Yu
- Neil Horman
- Pavel Zhukov
- Richard Purdie
- Robert Joslyn
- Ross Burton
- Ruiqiang Hao
- Samuli Piippo
- Steve Sakoman
- Sundeep KOKKONDA
- Teoh Jay Shen
- Tim Orling
- Virendra Thakur
- Vyacheslav Yurkov
- Xiangyu Chen
- Yash Shinde
- pgowda
- Wang Mingyu

## Repositories / Downloads for Yocto-4.0.5

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.5](#)
- Git Revision: [2e79b199114b25d81bfaa029ccfb17676946d20d](#)
- Release Artefact: [poky-2e79b199114b25d81bfaa029ccfb17676946d20d](#)

- sha: 7bcf3f901d4c5677fc95944ab096e9e306f4c758a658dde5befd16861ad2b8ea
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.5/poky-2e79b199114b25d81bfaa029ccfb17676946d20d.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.5/poky-2e79b199114b25d81bfaa029ccfb17676946d20d.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: kirkstone
- Tag: yocto-4.0.5
- Git Revision: fbdf93f43ff4b876487e1f26752598ec8abcb46e
- Release Artefact: oecore-fbdf93f43ff4b876487e1f26752598ec8abcb46e
- sha: 2d9b5a8e9355b633bb57633cc8c2d319ba13fe4721f79204e61116b3faa6cbf1
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.5/oecore-fbdf93f43ff4b876487e1f26752598ec8abcb46e.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.5/oecore-fbdf93f43ff4b876487e1f26752598ec8abcb46e.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.5
- Git Revision: a90614a6498c3345704e9611f2842eb933dc51c1
- Release Artefact: meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1
- sha: 49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.5/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.5/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.5
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.5/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.5/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.5
- Git Revision: c90d57497b9bcd237c3ae810ee8edb5b0d2d575a
- Release Artefact: bitbake-c90d57497b9bcd237c3ae810ee8edb5b0d2d575a
- sha: 5698d548ce179036e46a24f80b213124c8825a4f443fa1d6be7ab0f70b01a9ff
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.5/bitbake-c90d57497b9bcd237c3ae810ee8edb5b0d2d575a.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.5/bitbake-c90d57497b9bcd237c3ae810ee8edb5b0d2d575a.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.5
- Git Revision: 8c2f9f54e29781f4ee72e81eeaa12ceaa82dc2d3

### 17.11.8 Release notes for Yocto-4.0.6 (Kirkstone)

#### Security Fixes in Yocto-4.0.6

- bash: Fix CVE-2022-3715
- curl: Fix CVE-2022-32221, CVE-2022-42915 and CVE-2022-42916
- dbus: Fix CVE-2022-42010, CVE-2022-42011 and CVE-2022-42012
- dropbear: Fix CVE-2021-36369
- ffmpeg: Fix CVE-2022-3964, CVE-2022-3965
- go: Fix CVE-2022-2880
- grub2: Fix CVE-2022-2601, CVE-2022-3775 and CVE-2022-28736
- libarchive: Fix CVE-2022-36227
- libpam: Fix CVE-2022-28321
- libsndfile1: Fix CVE-2021-4156
- lighttpd: Fix CVE-2022-41556
- openssl: Fix CVE-2022-3358
- pixman: Fix CVE-2022-44638
- python3-mako: Fix CVE-2022-40023
- python3: Fix CVE-2022-42919
- qemu: Fix CVE-2022-3165

- sysstat: Fix [CVE-2022-39377](#)
- systemd: Fix [CVE-2022-3821](#)
- tiff: Fix [CVE-2022-2953](#), [CVE-2022-3599](#), [CVE-2022-3597](#), [CVE-2022-3626](#), [CVE-2022-3627](#), [CVE-2022-3570](#), [CVE-2022-3598](#) and [CVE-2022-3970](#)
- vim: Fix [CVE-2022-3352](#), [CVE-2022-3705](#) and [CVE-2022-4141](#)
- wayland: Fix [CVE-2021-3782](#)
- xserver-xorg: Fix [CVE-2022-3550](#) and [CVE-2022-3551](#)

### Fixes in Yocto-4.0.6

- archiver: avoid using machine variable as it breaks multiconfig
- babeltrace: upgrade to 1.5.11
- bind: upgrade to 9.18.8
- bitbake.conf: Drop export of SOURCE\_DATE\_EPOCH\_FALLBACK
- bitbake: git-sm: Fix regression in git-sm submodule path parsing
- bitbake: runqueue: Fix race issues around hash equivalence and sstate reuse
- bluez5: Point hciattach bcm43xx firmware search path to /lib/firmware
- bluez5: add dbus to RDEPENDS
- build-appliance-image: Update to kirkstone head revision
- buildtools-tarball: export certificates to python and curl
- cargo\_common.bbclass: Fix typos
- classes: make TOOLCHAIN more permissive for kernel
- cmake-native: Fix host tool contamination (Bug: 14951)
- common-tasks.rst: fix oeqa runtime test path
- create-spdx.bbclass: remove unused SPDX\_INCLUDE\_PACKAGED
- create-spdx: Remove ";name=..." for downloadLocation
- create-spdx: default share\_src for shared sources
- cve-update-db-native: add timeout to urlopen() calls
- dbus: upgrade to 1.14.4
- dhcpcd: fix to work with systemd
- expat: upgrade to 2.5.0
- externalsrc.bbclass: Remove a trailing slash from \${B}
- externalsrc.bbclass: fix git repo detection
- externalsrc: git submodule--helper list unsupported

- gcc-shared-source: Fix source date epoch handling
- gcc-source: Drop gengtype manipulation
- gcc-source: Ensure deploy\_source\_date\_epoch sstate hash doesn't change
- gcc-source: Fix gengtypes race
- gdk-pixbuf: upgrade to 2.42.10
- get\_module\_deps3.py: Check attribute '\_\_file\_\_'
- glib-2.0: fix rare GFileInfo test case failure
- glibc-locale: Do not INHIBIT\_DEFAULT\_DEPS
- gnomebase.bbclass: return the whole version for tarball directory if it is a number
- gnutls: Unified package names to lower-case
- groff: submit patches upstream
- gstreamer1.0-libav: fix errors with ffmpeg 5.x
- gstreamer1.0: upgrade to 1.20.4
- ifupdown: upgrade to 0.8.39
- insane.bbclass: Allow hashlib version that only accepts one parameter
- iso-codes: upgrade to 4.12.0
- kea: submit patch upstream (fix-multilib-conflict.patch)
- kern-tools: fix relative path processing
- kern-tools: integrate ZFS speedup patch
- kernel-yocto: improve fatal error messages of symbol\_why.py
- kernel.bbclass: Include randstruct seed assets in STAGING\_KERNEL\_BUILDDIR
- kernel.bbclass: make KERNEL\_DEBUG\_TIMESTAMPS work at rebuild
- kernel: Clear SYSROOT\_DIRS instead of replacing sysroot\_stage\_all
- libcap: upgrade to 2.66
- libepoxy: convert to git
- libepoxy: update to 1.5.10
- libffi: submit patch upstream (0001-arm-sysv-reverted-clang-VFP-mitigation.patch )
- libffi: upgrade to 3.4.4
- libical: upgrade to 3.0.16
- libksba: upgrade to 1.6.2
- libuv: fixup SRC\_URI
- libxcrypt: upgrade to 4.4.30

- lighttpd: upgrade to 1.4.67
- linux-firmware: add new fw file to \${PN}-qcom-adreno-a530
- linux-firmware: don't put the firmware into the sysroot
- linux-firmware: package amdgpu firmware
- linux-firmware: split rtl8761 firmware
- linux-firmware: upgrade to 20221109
- linux-yocto/5.10: update genericx86\* machines to v5.10.149
- linux-yocto/5.15: fix CONFIG\_CRYPTOC\_CCM mismatch warnings
- linux-yocto/5.15: update genericx86\* machines to v5.15.72
- linux-yocto/5.15: update to v5.15.78
- ltp: backport clock\_gettime04 fix from upstream
- lttnng-modules: upgrade to 2.13.7
- lttnng-tools: Upgrade to 2.13.8
- lttnng-tools: submit determinism.patch upstream
- lttnng-ust: upgrade to 2.13.5
- meson: make wrapper options sub-command specific
- meta-selftest/staticids: add render group for systemd
- mirrors.bbclass: update CPAN\_MIRROR
- mirrors.bbclass: use shallow tarball for binutils-native
- mobile-broadband-provider-info: upgrade 20220725 -> 20221107
- mtd-utils: upgrade 2.1.4 -> 2.1.5
- numactl: upgrade to 2.0.16
- oe/packagemanager/rpm: don't leak file objects
- oeqa/selftest/lic\_checksum: Cleanup changes to emptytest include
- oeqa/selftest/minidebuginfo: Create selftest for minidebuginfo
- oeqa/selftest/tinfoil: Add test for separate config\_data with recipe\_parse\_file()
- openssl: Fix SSL\_CERT\_FILE to match ca-certs location
- openssl: upgrade to 3.0.7
- openssl: export necessary env vars in SDK
- opkg-utils: use a git clone, not a dynamic snapshot
- opkg: Set correct info\_dir and status\_file in opkg.conf
- overlaysfs: Allow not used mount points



- ovmf: correct patches status
- package: Fix handling of minidebuginfo with newer binutils
- perf: Depend on native setuptools3
- poky.conf: bump version for 4.0.6
- psplash: add psplash-default in rdepends
- psplash: consider the situation of psplash not exist for systemd
- python3: advance to version 3.10.8
- qemu-helper-native: Correctly pass program name as argv[0]
- qemu-helper-native: Re-write bridge helper as C program
- qemu-native: Add PACKAGECONFIG option for jack
- qemu: add io\_uring PACKAGECONFIG
- quilt: backport a patch to address grep 3.8 failures
- resolvconf: make it work
- rm\_work: exclude the SSTATETASKS from the rm\_work tasks sinature
- runqemu: Do not perturb script environment
- runqemu: Fix gl-es argument from causing other arguments to be ignored
- sanity: Drop data finalize call
- sanity: check for GNU tar specifically
- scripts/oe-check-sstate: cleanup
- scripts/oe-check-sstate: force build to run for all targets, specifically populate\_sysroot
- scripts: convert-overrides: Allow command-line customizations
- socat: upgrade to 1.7.4.4
- SPDX and CVE documentation updates
- sstate: Allow optimisation of do\_deploy\_archives task dependencies
- sstatesig: emit more helpful error message when not finding sstate manifest
- sstatesig: skip the rm\_work task signature
- sudo: upgrade to 1.9.12p1
- systemd: Consider PACKAGECONFIG in RRECOMMENDS
- systemd: add group render to udev package
- tcl: correct patch status
- tiff: refresh with devtool
- tiff: add CVE tag to b258ed69a485a9cfb299d9f060eb2a46c54e5903.patch

- u-boot: Remove duplicate inherit of cml1
- uboot-sign: Fix using wrong KEY\_REQ\_ARGS
- vala: install vapigen-wrapper into /usr/bin/crosscripts and stage only that
- valgrind: remove most hidden tests for arm64
- vim: Upgrade to 9.0.0947
- vulkan-samples: add lfs=0 to SRC\_URI to avoid git smudge errors in do\_unpack
- wic: honor the SOURCE\_DATE\_EPOCH in case of updated fstab
- wic: make ext2/3/4 images reproducible
- wic: swap partitions are not added to fstab
- wpebackend-fdo: upgrade to 1.14.0
- xserver-xorg: move some recommended dependencies in required
- xwayland: upgrade to 22.1.5

#### **Known Issues in Yocto-4.0.6**

- N/A

#### **Contributors to Yocto-4.0.6**

- Alex Kiernan
- Alexander Kanavin
- Alexey Smirnov
- Bartosz Golaszewski
- Bernhard Rosenkränzer
- Bhabu Bindu
- Bruce Ashfield
- Chee Yang Lee
- Chen Qi
- Christian Eggers
- Claus Stovgaard
- Diego Sueiro
- Dmitry Baryshkov
- Ed Tanous
- Enrico Jörns
- Etienne Cordonnier
- Frank de Brabander

- Harald Seiler
- Hitendra Prajapati
- Jan-Simon Moeller
- Jeremy Puhlman
- Joe Slater
- John Edward Broadbent
- Jose Quaresma
- Joshua Watt
- Kai Kang
- Keiya Nobuta
- Khem Raj
- Konrad Weihmann
- Leon Anavi
- Liam Beguin
- Marek Vasut
- Mark Hatle
- Martin Jansa
- Michael Opdenacker
- Mikko Rapeli
- Narpat Mali
- Nathan Rossi
- Niko Mauno
- Pavel Zhukov
- Peter Kjellerstedt
- Peter Marko
- Polampalli, Archana
- Qiu, Zheng
- Ravula Adhitya Siddartha
- Richard Purdie
- Ross Burton
- Sakib Sajal
- Sean Anderson

- Sergei Zhmylev
- Steve Sakoman
- Teoh Jay Shen
- Thomas Perrot
- Tim Orling
- Vincent Davis Jr
- Vivek Kumbhar
- Vyacheslav Yurkov
- Wang Mingyu
- Xiangyu Chen
- Zheng Qiu
- Ciaran Courtney
- Wang Mingyu

## Repositories / Downloads for Yocto-4.0.6

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.6](#)
- Git Revision: [c4e08719a782fd4119eaf643907b80cebf57f88f](#)
- Release Artefact: [poky-c4e08719a782fd4119eaf643907b80cebf57f88f](#)
- sha: [2eb3b323dd2ccd25f9442bfbcbbde82bc081fad5afd146a8e6dde439db24a99d4](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.6/poky-c4e08719a782fd4119eaf643907b80cebf57f88f.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.6/poky-c4e08719a782fd4119eaf643907b80cebf57f88f.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.6](#)
- Git Revision: [45a8b4101b14453aa3020d3f2b8a76b4dc0ae3f2](#)
- Release Artefact: [oecore-45a8b4101b14453aa3020d3f2b8a76b4dc0ae3f2](#)
- sha: [de8b443365927befe67cc443b60db57563ff0726377223f836a3f3971cf405ec](#)

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.6/oecore-45a8b4101b14453aa3020d3f2b8a76b4dc0ae3f2.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.6/oecore-45a8b4101b14453aa3020d3f2b8a76b4dc0ae3f2.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.6`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.6/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.6/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.6`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.6/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.6/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.6`
- Git Revision: `7e268c107bb0240d583d2c34e24a71e373382509`
- Release Artefact: `bitbake-7e268c107bb0240d583d2c34e24a71e373382509`
- sha: `c3e2899012358c95962c7a5c85cf98dc30c58eae0861c374124e96d9556bb901`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.6/bitbake-7e268c107bb0240d583d2c34e24a71e373382509.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.6/bitbake-7e268c107bb0240d583d2c34e24a71e373382509.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>

- Branch: [kirkstone](#)
- Tag: [yocto-4.0.6](#)
- Git Revision: [c10d65ef3bbdf4fe3abc03e3aef3d4ca8c2ad87f](#)

### 17.11.9 Release notes for Yocto-4.0.7 (Kirkstone)

#### Security Fixes in Yocto-4.0.7

- binutils: Fix [CVE-2022-4285](#)
- curl: Fix [CVE-2022-43551](#) and [CVE-2022-43552](#)
- ffmpeg: Fix [CVE-2022-3109](#) and [CVE-2022-3341](#)
- go: Fix [CVE-2022-41715](#) and [CVE-2022-41717](#)
- libX11: Fix [CVE-2022-3554](#) and [CVE-2022-3555](#)
- libarchive: Fix [CVE-2022-36227](#)
- libksba: Fix [CVE-2022-47629](#)
- libpng: Fix [CVE-2019-6129](#)
- libxml2: Fix [CVE-2022-40303](#) and [CVE-2022-40304](#)
- openssl: Fix [CVE-2022-3996](#)
- python3: Fix [CVE-2022-45061](#)
- python3-git: Fix [CVE-2022-24439](#)
- python3-setuptools: Fix [CVE-2022-40897](#)
- python3-wheel: Fix [CVE-2022-40898](#)
- qemu: Fix [CVE-2022-4144](#)
- sqlite: Fix [CVE-2022-46908](#)
- systemd: Fix [CVE-2022-45873](#)
- vim: Fix [CVE-2023-0049](#), [CVE-2023-0051](#), [CVE-2023-0054](#) and [CVE-2023-0088](#)
- webkitgtk: Fix [CVE-2022-32886](#), [CVE-2022-32891](#) and [CVE-2022-32912](#)

#### Fixes in Yocto-4.0.7

- Revert "gststreamer1.0: disable flaky gstbin:test\_watch\_for\_state\_change test"
- at: Change when files are copied
- baremetal-image: Avoid overriding qemu variables from IMAGE\_CLASSES
- base.bbclass: Fix way to check ccache path
- bc: extend to nativesdk
- bind: upgrade to 9.18.10

- busybox: always start do\_compile with orig config files
- busybox: rm temporary files if do\_compile was interrupted
- cairo: fix CVE patches assigned wrong CVE number
- cairo: update patch for [CVE-2019-6461](#) with upstream solution
- classes/create-spdx: Add SPDX\_PRETTY option
- classes: image: Set empty weak default IMAGE\_LINGUAS
- combo-layer: add sync-revs command
- combo-layer: dont use bb.utils.rename
- combo-layer: remove unused import
- curl: Correct LICENSE from MIT-open-group to curl
- cve-check: write the cve manifest to IMGDEPLOYDIR
- cve-update-db-native: avoid incomplete updates
- cve-update-db-native: show IP on failure
- dbus: Add missing CVE product name
- devtool/upgrade: correctly handle recipes where S is a subdir of upstream tree
- devtool: process local files only for the main branch
- dhcpcd: backport two patches to fix runtime error
- docs: kernel-dev: faq: update tip on how to not include kernel in image
- docs: migration-4.0: specify variable name change for kernel inclusion in image recipe
- efibootmgr: update compilation with musl
- externalsrc: fix lookup for .gitmodules
- ffmpeg: refresh patches to apply cleanly
- freetype:update mirror site.
- gcc: Refactor linker patches and fix linker on arm with usrmerge
- glibc: stable 2.35 branch updates.
- go-crosssdk: avoid host contamination by GOCACHE
- gstreamer1.0: Fix race conditions in gstbin tests
- gstreamer1.0: upgrade to 1.20.5
- gtk-icon-cache: Fix GTKIC\_CMD if-else condition
- harfbuzz: remove bindir only if it exists
- kernel-fitimage: Adjust order of dtb/dtbo files
- kernel-fitimage: Allow user to select dtb when multiple dtb exists

- kernel.bbclass: remove empty module directories to prevent QA issues
- lib/buildstats: fix parsing of trees with reduced\_proc\_pressure directories
- lib/oe/reproducible: Use git log without gpg signature
- libepoxy: remove upstreamed patch
- libnewt: update 0.52.21 -> 0.52.23
- libseccomp: fix typo in DESCRIPTION
- libxcrypt-compat: upgrade 4.4.30 -> 4.4.33
- libxml2: fix test data checksums
- linux-firmware: upgrade 20221109 -> 20221214
- linux-yocto/5.10: update to v5.10.152
- linux-yocto/5.10: update to v5.10.154
- linux-yocto/5.10: update to v5.10.160
- linux-yocto/5.15: fix perf build with clang
- linux-yocto/5.15: libbpf: Fix build warning on ref\_ctr\_off
- linux-yocto/5.15: ltp and squashfs fixes
- linux-yocto/5.15: powerpc: Fix reschedule bug in KUAP-unlocked user copy
- linux-yocto/5.15: update to v5.15.84
- lsof: add update-alternatives logic
- lttnng-modules: update 2.13.7 -> 2.13.8
- manuals: add 4.0.5 and 4.0.6 release notes
- manuals: document SPDX\_PRETTY variable
- mpfr: upgrade 4.1.0 -> 4.1.1
- oeqa/concurrencytest: Add number of failures to summary output
- oeqa/rpm.py: Increase timeout and add debug output
- oeqa/selftest/externalsrc: add test for srcree\_hash\_files
- openssh: remove RRECOMMENDS to rng-tools for sshd package
- poky.conf: bump version for 4.0.7
- qemu-boot.bbclass: make sure runqemu boots bundled initramfs kernel image
- rm\_work.bbclass: use HOSTTOOLS 'rm' binary exclusively
- rm\_work: adjust dependency to make do\_rm\_work\_all depend on do\_rm\_work
- ruby: merge .inc into .bb
- ruby: update 3.1.2 -> 3.1.3



- selftest/virgl: use pkg-config from the host
- tiff: Add packageconfig knob for webp
- toolchain-scripts: compatibility with unbound variable protection
- tzdata: update 2022d -> 2022g
- valgrind: skip the boost\_thread test on arm
- xserver-xorg: upgrade 21.1.4 -> 21.1.6
- xwayland: libxshmfence is needed when dri3 is enabled
- xwayland: upgrade 22.1.5 -> 22.1.7
- yocto-check-layer: Allow OE-Core to be tested

### Known Issues in Yocto-4.0.7

- N/A

### Contributors to Yocto-4.0.7

- Alejandro Hernandez Samaniego
- Alex Kiernan
- Alex Stewart
- Alexander Kanavin
- Antonin Godard
- Benoît Mauduit
- Bhabu Bindu
- Bruce Ashfield
- Carlos Alberto Lopez Perez
- Changqing Li
- Chen Qi
- Daniel Gomez
- Florin Diaconescu
- He Zhe
- Hitendra Prajapati
- Jagadeesh Krishnanjanappa
- Jan Kircher
- Jermain Horsman
- Jose Quaresma
- Joshua Watt

- KARN JYE LAU
- Kai Kang
- Khem Raj
- Luis
- Marta Rybczynska
- Martin Jansa
- Mathieu Dubois-Briand
- Michael Opdenacker
- Narpat Mali
- Ovidiu Panait
- Pavel Zhukov
- Peter Marko
- Petr Kubizňák
- Quentin Schulz
- Randy MacLeod
- Ranjitsinh Rathod
- Richard Purdie
- Robert Andersson
- Ross Burton
- Sandeep Gundlupet Raju
- Saul Wold
- Steve Sakoman
- Vivek Kumbhar
- Wang Mingyu
- Xiangyu Chen
- Yash Shinde
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.7

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.7](#)

- Git Revision: [65dafa22018052fe7b2e17e6e4d7eb754224d38](#)
- Release Artefact: poky-65dafa22018052fe7b2e17e6e4d7eb754224d38
- sha: 6b1b67600b84503e2d5d29bcd6038547339f4f9413b830cd2408df825eda642d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.7/poky-65dafa22018052fe7b2e17e6e4d7eb754224d38.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.7/poky-65dafa22018052fe7b2e17e6e4d7eb754224d38.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.7](#)
- Git Revision: [a8c82902384f7430519a31732a4bb631f21693ac](#)
- Release Artefact: oecore-a8c82902384f7430519a31732a4bb631f21693ac
- sha: 6f2dbc4ea1e388620ef77ac3a7bbb2b5956bb8bf9349b0c16cd7610e9996f5ea
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.7/oecore-a8c82902384f7430519a31732a4bb631f21693ac.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.7/oecore-a8c82902384f7430519a31732a4bb631f21693ac.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.7](#)
- Git Revision: [a90614a6498c3345704e9611f2842eb933dc51c1](#)
- Release Artefact: meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1
- sha: 49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.7/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.7/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.7](#)
- Git Revision: [d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.7/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>   <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.7/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.7
- Git Revision: 7e268c107bb0240d583d2c34e24a71e373382509
- Release Artefact: bitbake-7e268c107bb0240d583d2c34e24a71e373382509
- sha: c3e2899012358c95962c7a5c85cf98dc30c58eae0861c374124e96d9556bb901
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.7/bitbake-7e268c107bb0240d583d2c34e24a71e373382509.tar.bz2>   <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.7/bitbake-7e268c107bb0240d583d2c34e24a71e373382509.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.7
- Git Revision: 5883e897c34f25401b358a597fb6e18d80f7f90b

### 17.11.10 Release notes for Yocto-4.0.8 (Kirkstone)

#### Security Fixes in Yocto-4.0.8

- apr-util: Fix CVE-2022-25147
- apr: Fix CVE-2022-24963, CVE-2022-28331 and CVE-2021-35940
- bind: Fix CVE-2022-3094, CVE-2022-3736 and CVE-2022-3924
- git: Ignore CVE-2022-41953
- git: Fix CVE-2022-23521 and CVE-2022-41903
- libgit2: Fix CVE-2023-22742
- ppp: Fix CVE-2022-4603
- python3-certifi: Fix CVE-2022-23491
- sudo: Fix CVE-2023-22809
- tar: Fix CVE-2022-48303

## Fixes in Yocto-4.0.8

- core-image.bbclass: Fix missing leading whitespace with ':append'
- populate\_sdk\_ext.bbclass: Fix missing leading whitespace with ':append'
- ptest-packagelists.inc: Fix missing leading whitespace with ':append'
- apr-util: upgrade to 1.6.3
- apr: upgrade to 1.7.2
- apt: fix do\_package\_qa failure
- bind: upgrade to 9.18.11
- bitbake: bb/utis: include SSL certificate paths in export\_proxies
- bitbake: bitbake-diffsigs: Make PEP8 compliant
- bitbake: bitbake-diffsigs: break on first dependent task difference
- bitbake: fetch2/git: Clarify the meaning of namespace
- bitbake: fetch2/git: Prevent git fetcher from fetching gitlab repository metadata
- bitbake: fetch2/git: show SRCREV and git repo in error message about fixed SRCREV
- bitbake: siggen: Fix inefficient string concatenation
- bitbake: utils/ply: Update md5 to better report errors with hashlib
- bootchart2: Fix usrmerge support
- bsp-guide: fix broken git URLs and missing word
- build-appliance-image: Update to kirkstone head revision
- buildtools-tarball: set pkg-config search path
- classes/fs-uuid: Fix command output decoding issue
- dev-manual: common-tasks.rst: add link to FOSDEM 2023 video
- dev-manual: fix old override syntax
- devshell: Do not add scripts/git-intercept to PATH
- devtool: fix devtool finish when gitmodules file is empty
- diffutils: upgrade to 3.9
- gdk-pixbuf: do not use tools from gdk-pixbuf-native when building tests
- git: upgrade to 2.35.7
- glslang: branch rename master -> main
- httpserver: add error handler that write to the logger
- image.bbclass: print all QA functions exceptions
- kernel/linux-kernel-base: Fix kernel build artefact determinism issues

- libc-locale: Fix on target locale generation
- libgit2: upgrade to 1.4.5
- libjpeg-turbo: upgrade to 2.1.5
- libtirpc: Check if file exists before operating on it
- libusb1: Link with latomic only if compiler has no atomic builtins
- libusb1: Strip trailing whitespaces
- linux-firmware: upgrade to 20230117
- linux-yocto/5.15: update to v5.15.91
- lsof: fix old override syntax
- lttnng-modules: Fix for 5.10.163 kernel version
- lttnng-tools: upgrade to 2.13.9
- make-mod-scripts: Ensure kernel build output is deterministic
- manuals: update patchwork instance URL
- meta: remove True option to getVar and getVarFlag calls (again)
- migration-guides: add release-notes for 4.0.7
- native: Drop special variable handling
- numactl: skip test case when target platform doesn't have 2 CPU node
- oeqa context.py: fix --target-ip comment to include ssh port number
- oeqa dump.py: add error counter and stop after 5 failures
- oeqa qemurunner.py: add timeout to QMP calls
- oeqa qemurunner.py: try to avoid reading one character at a time
- oeqa qemurunner: read more data at a time from serial
- oeqa ssh.py: add connection keep alive options to ssh client
- oeqa ssh.py: move output prints to new line
- oeqa/qemurunner: do not use Popen.poll() when terminating runqemu with a signal
- oeqa/selftest/bbtests: Update message lookup for test\_git\_unpack\_nonetwork\_fail
- oeqa/selftest/locales: Add selftest for locale generation/presence
- poky.conf: Update SANITY\_TESTED\_DISTROS to match autobuilder
- poky.conf: bump version for 4.0.8
- profile-manual: update WireShark hyperlinks
- python3-pytest: depend on python3-tomli instead of python3-toml
- qemu: fix compile error

- quilt: fix intermittent failure in faildiff.test
- quilt: use upstreamed faildiff.test fix
- recipe\_sanity: fix old override syntax
- ref-manual: document SSTATE\_EXCLUDEDEPS\_SYSROOT
- scons.bbclass: Make MAXLINELENGTH overridable
- scons: Pass MAXLINELENGTH to scons invocation
- sdkext/cases/devtool: pass a logger to HTTPService
- spirv-headers: set correct branch name
- sudo: upgrade to 1.9.12p2
- system-requirements.rst: add Fedora 36 and AlmaLinux 8.7 to list of supported distros
- testimage: Fix error message to reflect new syntax
- update-alternatives: fix typos
- vulkan-samples: branch rename master -> main

#### Known Issues in Yocto-4.0.8

- N/A

#### Contributors to Yocto-4.0.8

- Alejandro Hernandez Samaniego
- Alexander Kanavin
- Alexandre Belloni
- Armin Kuster
- Arnout Vandecappelle
- Bruce Ashfield
- Changqing Li
- Chee Yang Lee
- Etienne Cordonnier
- Harald Seiler
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Louis Rannou
- Marek Vasut
- Marius Kriegerowski

- Mark Hatle
- Martin Jansa
- Mauro Queiros
- Michael Opdenacker
- Mikko Rapeli
- Mingli Yu
- Narpat Mali
- Niko Mauno
- Pawel Zalewski
- Peter Kjellerstedt
- Richard Purdie
- Rodolfo Quesada Zumbado
- Ross Burton
- Sakib Sajal
- Schmidt, Adriaan
- Steve Sakoman
- Thomas Roos
- Ulrich Ölmann
- Xiangyu Chen

## Repositories / Downloads for Yocto-4.0.8

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.8](#)
- Git Revision: [a361fb3df9c87cf12963a9d785a9f99faa839222](#)
- Release Artefact: [poky-a361fb3df9c87cf12963a9d785a9f99faa839222](#)
- sha: [af4e8d64be27d3a408357c49b7952ce04c6d8bb0b9d7b50c48848d9355de7fc2](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.8/poky-a361fb3df9c87cf12963a9d785a9f99faa839222.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.8/poky-a361fb3df9c87cf12963a9d785a9f99faa839222.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)



- Tag: `yocto-4.0.8`
- Git Revision: `b20e2134daec33fbb8ce358d984751d887752bd5`
- Release Artefact: `oecore-b20e2134daec33fbb8ce358d984751d887752bd5`
- sha: `63cce6f1caf8428eefc1471351ab024affc8a41d8d7777f525e3aa9ea454d2cd`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.8/oecore-b20e2134daec33fbb8ce358d984751d887752bd5.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.8/oecore-b20e2134daec33fbb8ce358d984751d887752bd5.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.8`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.8/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.8/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.8`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.8/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.8/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.8`
- Git Revision: `9bbdedc0ba7ca819b898e2a29a151d6a2014ca11`
- Release Artefact: `bitbake-9bbdedc0ba7ca819b898e2a29a151d6a2014ca11`
- sha: `8e724411f4df00737e81b33eb568f1f97d2a00d5364342c0a212c46abb7b005b`

- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.8/bitbake-9bbdedc0ba7ca819b898e2a29a151d6a2014ca11.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.8/bitbake-9bbdedc0ba7ca819b898e2a29a151d6a2014ca11.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.8`
- Git Revision: `16ecbe028f2b9cc021267817a5413054e070b563`

### 17.11.11 Release notes for Yocto-4.0.9 (Kirkstone)

#### Security Fixes in Yocto-4.0.9

- binutils: Fix CVE-2023-22608
- curl: Fix CVE-2023-23914, CVE-2023-23915 and CVE-2023-23916
- epiphany: Fix CVE-2023-26081
- git: Ignore CVE-2023-22743
- glibc: Fix CVE-2023-0687
- gnutls: Fix CVE-2023-0361
- go: Fix CVE-2022-2879, CVE-2022-41720 and CVE-2022-41723
- harfbuzz: Fix CVE-2023-25193
- less: Fix CVE-2022-46663
- libmicrohttpd: Fix CVE-2023-27371
- libsdl2: Fix CVE-2022-4743
- openssl: Fix CVE-2022-3996, CVE-2023-0464, CVE-2023-0465 and CVE-2023-0466
- pkgconf: Fix CVE-2023-24056
- python3: Fix CVE-2023-24329
- shadow: Ignore CVE-2016-15024
- systemd: Fix CVE-2022-4415
- tiff: Fix CVE-2023-0800, CVE-2023-0801, CVE-2023-0802, CVE-2023-0803 and CVE-2023-0804
- vim: Fix CVE-2023-0433, CVE-2023-0512, CVE-2023-1127, CVE-2023-1170, CVE-2023-1175, CVE-2023-1264 and CVE-2023-1355
- xserver-xorg: Fix CVE-2023-0494
- xwayland: Fix CVE-2023-0494

## Fixes in Yocto-4.0.9

- base-files: Drop localhost.localdomain from hosts file
- binutils: Fix nativesdk ld.so search
- bitbake: cookerdata: Drop dubious exception handling code
- bitbake: cookerdata: Improve early exception handling
- bitbake: cookerdata: Remove incorrect SystemExit usage
- bitbake: fetch/git: Fix local clone url to make it work with repo
- bitbake: utils: Allow to\_boolean to support int values
- bmap-tools: switch to main branch
- buildtools-tarball: Handle spaces within user \$PATH
- busybox: Fix depmod patch
- cracklib: update github branch to 'main'
- cups: add/fix web interface packaging
- cups: check PACKAGECONFIG for pam feature
- cups: use BUILDROOT instead of DESTDIR
- curl: fix dependencies when building with ldap/ldaps
- cve-check: Fix false negative version issue
- dbus: upgrade to 1.14.6
- devtool/upgrade: do not delete the workspace/recipes directory
- dhcpcd: Fix install conflict when enable multilib.
- dhcpcd: fix dhcpcd start failure on qemuppc64
- gcc-shared-source: do not use \${S}/.. in deploy\_source\_date\_epoch
- glibc: Add missing binutils dependency
- image\_types: fix multiubi var init
- iso-codes: upgrade to 4.13.0
- json-c: Add ptest for json-c
- kernel-yocto: fix kernel-meta data detection
- lib/buildstats: handle tasks that never finished
- lib/resulttool: fix typo breaking resulttool log --ptest
- libjpeg-turbo: upgrade to 2.1.5.1
- libmicrohttpd: upgrade to 0.9.76
- libseccomp: fix for the ptest result format

- libssh2: Clean up ptest patch/coverage
- linux-firmware: add yamato fw files to qcom-adreno-a2xx package
- linux-firmware: properly set license for all Qualcomm firmware
- linux-firmware: upgrade to 20230210
- linux-yocto-rt/5.15: update to -rt59
- linux-yocto/5.10: upgrade to v5.10.175
- linux-yocto/5.15: upgrade to v5.15.103
- linux: inherit pkgconfig in kernel.bbclass
- lttnng-modules: fix for kernel 6.2+
- lttnng-modules: upgrade to v2.13.9
- lua: Fix install conflict when enable multilib.
- mdadm: Fix raid0, 06wrmotly and 02lineargrow tests
- meson: Fix wrapper handling of implicit setup command
- migration-guides: add 4.0.8 release notes
- nhttp2: never build python bindings
- oeqa rtc.py: skip if read-only-rootfs
- oeqa ssh.py: fix hangs in run()
- oeqa/sdk: Improve Meson test
- oeqa/selftest/prservice: Improve debug output for failure
- oeqa/selftest/resulttooltests: fix minor typo
- openssl: upgrade to 3.0.8
- package.bbclase: Add check for /build in copydebugsources()
- patchelf: replace a rejected patch with an equivalent uninative.bbclass tweak
- poky.conf: bump version for 4.0.9
- populate\_sdk\_ext: Handle spaces within user \$PATH
- pybootchartui: Fix python syntax issue
- python3-git: fix indent error
- python3-setuptools-rust-native: Add direct dependency of native python3 modules
- qemu: Revert "fix [CVE-2021-3507](#)" as not applicable for qemu 6.2
- rsync: Add missing prototypes to function declarations
- rsync: Turn on -pedantic-errors at the end of 'configure'
- runqemu: kill qemu if it hangs

- scripts/lib/buildstats: handle top-level build\_stats not being complete
- selftest/recipe tool: Stop test corrupting tinfoil class
- selftest/runtime\_test/virgl: Disable for all Rocky Linux
- selftest: devtool: set BB\_HASHSERVE\_UPSTREAM when setting SSTATE\_MIRROR
- sstatesig: Improve output hash calculation
- staging/multilib: Fix manifest corruption
- staging: Separate out different multiconfig manifests
- sudo: update 1.9.12p2 -> 1.9.13p3
- systemd.bbclass: Add /usr/lib/systemd to searchpaths as well
- systemd: add group sgx to udev package
- systemd: fix wrong nobody-group assignment
- timezone: use 'tz' subdir instead of \${WORKDIR} directly
- toolchain-scripts: Handle spaces within user \$PATH
- tzcode-native: fix build with gcc-13 on host
- tzdata: use separate B instead of WORKDIR for zic output
- uninative: upgrade to 3.9 to include libgcc and glibc 2.37
- vala: Fix install conflict when enable multilib.
- vim: add missing pkgconfig inherit
- vim: set modified-by to the recipe MAINTAINER
- vim: upgrade to 9.0.1429
- wic: Fix usage of fstype=none in wic
- wireless-regdb: upgrade to 2023.02.13
- xserver-xorg: upgrade to 21.1.7
- xwayland: upgrade to 22.1.8

### Known Issues in Yocto-4.0.9

- N/A

### Contributors to Yocto-4.0.9

- Alexander Kanavin
- Alexis Lothoré
- Bruce Ashfield
- Changqing Li
- Chee Yang Lee

- Dmitry Baryshkov
- Federico Pellegrin
- Geoffrey GIRY
- Hitendra Prajapati
- Hongxu Jia
- Joe Slater
- Kai Kang
- Kenfe-Mickael Laventure
- Khem Raj
- Martin Jansa
- Mateusz Marciniec
- Michael Halstead
- Michael Opdenacker
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Narpat Mali
- Pavel Zhukov
- Pawan Badganchi
- Peter Marko
- Piotr Łobacz
- Poonam Jadhav
- Randy MacLeod
- Richard Purdie
- Robert Yang
- Romuald Jeanne
- Ross Burton
- Sakib Sajal
- Saul Wold
- Shubham Kulkarni
- Siddharth Doshi
- Simone Weiss

- Steve Sakoman
- Tim Orling
- Tom Hochstein
- Trevor Woerner
- Ulrich Ölmann
- Vivek Kumbhar
- Wang Mingyu
- Xiangyu Chen
- Yash Shinde

## Repositories / Downloads for Yocto-4.0.9

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.9](#)
- Git Revision: [09def309f91929f47c6cce386016ccb777bd2cfc](#)
- Release Artefact: [poky-09def309f91929f47c6cce386016ccb777bd2cfc](#)
- sha: [5c7ce209c8a6b37ec2898e5ca21858234d91999c11fa862880ba98e8bde62f63](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.9/poky-09def309f91929f47c6cce386016ccb777bd2cfc.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.9/poky-09def309f91929f47c6cce386016ccb777bd2cfc.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.9](#)
- Git Revision: [ff4b57fff903a93b710284c7c7f916ddd74712f](#)
- Release Artefact: [oecore-ff4b57fff903a93b710284c7c7f916ddd74712f](#)
- sha: [726778ffc291136db1704316b196de979f68df9f96476b785e1791957fbb66b3](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.9/oecore-ff4b57fff903a93b710284c7c7f916ddd74712f.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.9/oecore-ff4b57fff903a93b710284c7c7f916ddd74712f.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [kirkstone](#)

- Tag: `yocto-4.0.9`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.9/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.9/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.9`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.9/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.9/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.9`
- Git Revision: `2802adb572eb73a3eb2725a74a9bbdaafc543fa7`
- Release Artefact: `bitbake-2802adb572eb73a3eb2725a74a9bbdaafc543fa7`
- sha: `5c6e713b5e26b3835c0773095c7a1bc1f8affa28316b33597220ed86f1f1b643`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.9/bitbake-2802adb572eb73a3eb2725a74a9bbdaafc543fa7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.9/bitbake-2802adb572eb73a3eb2725a74a9bbdaafc543fa7.tar.bz2>

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.9`
- Git Revision: `86d0b38a97941ad52b1af220c7b801a399d50e93`



## 17.11.12 Release notes for Yocto-4.0.10 (Kirkstone)

### Security Fixes in Yocto-4.0.10

- binutils: Fix CVE-2023-1579, CVE-2023-1972, CVE-2023-25584, CVE-2023-25585 and CVE-2023-25588
- cargo : Ignore CVE-2022-46176
- connman: Fix CVE-2023-28488
- curl: Fix CVE-2023-27533, CVE-2023-27534, CVE-2023-27535, CVE-2023-27536 and CVE-2023-27538
- ffmpeg: Fix CVE-2022-48434
- freetype: Fix CVE-2023-2004
- ghostscript: Fix CVE-2023-29979
- git: Fix CVE-2023-25652 and CVE-2023-29007
- go: Fix CVE-2022-41722, CVE-2022-41724, CVE-2022-41725, CVE-2023-24534, CVE-2023-24537 and CVE-2023-24538
- go: Ignore CVE-2022-41716
- libxml2: Fix CVE-2023-28484 and CVE-2023-29469
- libxpm: Fix CVE-2022-44617, CVE-2022-46285 and CVE-2022-4883
- linux-yocto: Ignore CVE-2021-3759, CVE-2021-4135, CVE-2021-4155, CVE-2022-0168, CVE-2022-0171, CVE-2022-1016, CVE-2022-1184, CVE-2022-1198, CVE-2022-1199, CVE-2022-1462, CVE-2022-1734, CVE-2022-1852, CVE-2022-1882, CVE-2022-1998, CVE-2022-2078, CVE-2022-2196, CVE-2022-2318, CVE-2022-2380, CVE-2022-2503, CVE-2022-26365, CVE-2022-2663, CVE-2022-2873, CVE-2022-2905, CVE-2022-2959, CVE-2022-3028, CVE-2022-3078, CVE-2022-3104, CVE-2022-3105, CVE-2022-3106, CVE-2022-3107, CVE-2022-3111, CVE-2022-3112, CVE-2022-3113, CVE-2022-3115, CVE-2022-3202, CVE-2022-32250, CVE-2022-32296, CVE-2022-32981, CVE-2022-3303, CVE-2022-33740, CVE-2022-33741, CVE-2022-33742, CVE-2022-33743, CVE-2022-33744, CVE-2022-33981, CVE-2022-3424, CVE-2022-3435, CVE-2022-34918, CVE-2022-3521, CVE-2022-3545, CVE-2022-3564, CVE-2022-3586, CVE-2022-3594, CVE-2022-36123, CVE-2022-3621, CVE-2022-3623, CVE-2022-3629, CVE-2022-3633, CVE-2022-3635, CVE-2022-3646, CVE-2022-3649, CVE-2022-36879, CVE-2022-36946, CVE-2022-3707, CVE-2022-39188, CVE-2022-39190, CVE-2022-39842, CVE-2022-40307, CVE-2022-40768, CVE-2022-4095, CVE-2022-41218, CVE-2022-4139, CVE-2022-41849, CVE-2022-41850, CVE-2022-41858, CVE-2022-42328, CVE-2022-42329, CVE-2022-42703, CVE-2022-42721, CVE-2022-42722, CVE-2022-42895, CVE-2022-4382, CVE-2022-4662, CVE-2022-47518, CVE-2022-47519, CVE-2022-47520, CVE-2022-47929, CVE-2023-0179, CVE-2023-0394, CVE-2023-0461, CVE-2023-0590, CVE-2023-1073, CVE-2023-1074, CVE-2023-1077, CVE-2023-1078, CVE-2023-1079, CVE-2023-1095, CVE-2023-1118, CVE-2023-1249, CVE-2023-1252, CVE-2023-1281, CVE-2023-1382, CVE-2023-1513, CVE-2023-1829, CVE-2023-1838, CVE-2023-1998, CVE-2023-2006, CVE-2023-2008, CVE-2023-2162, CVE-2023-2166, CVE-2023-2177, CVE-2023-22999, CVE-2023-23002, CVE-2023-23004, CVE-2023-23454, CVE-2023-23455, CVE-2023-23559, CVE-2023-25012, CVE-2023-26545, CVE-2023-28327 and CVE-2023-28328
- nasm: Fix CVE-2022-44370

- python3-cryptography: Fix [CVE-2023-23931](#)
- qemu: Ignore [CVE-2023-0664](#)
- ruby: Fix [CVE-2023-28755](#) and [CVE-2023-28756](#)
- screen: Fix [CVE-2023-24626](#)
- shadow: Fix [CVE-2023-29383](#)
- tiff: Fix [CVE-2022-4645](#)
- webkitgtk: Fix [CVE-2022-32888](#) and [CVE-2022-32923](#)
- xserver-xorg: Fix [CVE-2023-1393](#)

### Fixes in Yocto-4.0.10

- bitbake: bin/utlils: Ensure locale en\_US.UTF-8 is available on the system
- build-appliance-image: Update to kirkstone head revision
- cmake: add CMAKE\_SYSROOT to generated toolchain file
- glibc: stable 2.35 branch updates.
- kernel-devsrc: depend on python3-core instead of python3
- kernel: improve initramfs bundle processing time
- libarchive: Enable acls, xattr for native as well as target
- libbsd: Add correct license for all packages
- libpam: Fix the xtests/tst-pam\_motd[1|3] failures
- libxpm: upgrade to 3.5.15
- linux-firmware: upgrade to 20230404
- linux-yocto/5.15: upgrade to v5.15.108
- migration-guides: add release-notes for 4.0.9
- oeqa/utlils/metadata.py: Fix running oe-selftest running with no distro set
- openssl: Move microblaze to linux-latomic config
- package.bbclass: correct check for /build in copydebugsources()
- poky.conf: bump version for 4.0.10
- populate\_sdk\_base: add zip options
- populate\_sdk\_ext.bbclass: set *METADATA\_REVISION* with an *DISTRO* override
- run-postinsts: Set dependency for ldconfig to avoid boot issues
- update-alternatives.bbclass: fix old override syntax
- wic/bootimg-efi: if fixed-size is set then use that for mkdosfs
- wpebackend-fdo: upgrade to 1.14.2

- xorg-lib-common: Add variable to set tarball type
- xserver-xorg: upgrade to 21.1.8

### Known Issues in Yocto-4.0.10

- N/A

### Contributors to Yocto-4.0.10

- Archana Polampalli
- Arturo Buzarra
- Bruce Ashfield
- Christoph Lauer
- Deepthi Hemraj
- Dmitry Baryshkov
- Frank de Brabander
- Hitendra Prajapati
- Joe Slater
- Kai Kang
- Kyle Russell
- Lee Chee Yang
- Mark Hatle
- Martin Jansa
- Mingli Yu
- Narpat Mali
- Pascal Bach
- Pawan Badganchi
- Peter Bergin
- Peter Marko
- Piotr Łobacz
- Randolph Sapp
- Ranjitsinh Rathod
- Ross Burton
- Shubham Kulkarni
- Siddharth Doshi
- Steve Sakoman

- Sundeep KOKKONDA
- Thomas Roos
- Virendra Thakur
- Vivek Kumbhar
- Wang Mingyu
- Xiangyu Chen
- Yash Shinde
- Yoann Congal
- Yogita Urade
- Zhixiong Chi

## Repositories / Downloads for Yocto-4.0.10

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.10](#)
- Git Revision: [f53ab3a2ff206a130cdc843839dd0ea5ec4ad02f](#)
- Release Artefact: [poky-f53ab3a2ff206a130cdc843839dd0ea5ec4ad02f](#)
- sha: [8820aeac857ce6bbd1c7ef26cadbb86eca02be93deded253b4a5f07ddd69255d](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.10/poky-f53ab3a2ff206a130cdc843839dd0ea5ec4ad02f.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.10/poky-f53ab3a2ff206a130cdc843839dd0ea5ec4ad02f.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.10](#)
- Git Revision: [d2713785f9cd2d58731df877bc8b7bcc71b6c8e6](#)
- Release Artefact: [oecore-d2713785f9cd2d58731df877bc8b7bcc71b6c8e6](#)
- sha: [78e084a1aceaaa6ec022702f29f80eaffade3159e9c42b6b8985c1b7ddd2fbab](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.10/oecore-d2713785f9cd2d58731df877bc8b7bcc71b6c8e6.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.10/oecore-d2713785f9cd2d58731df877bc8b7bcc71b6c8e6.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>

- Branch: `kirkstone`
- Tag: `yocto-4.0.10`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.10/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.10/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.10`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.10/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.10/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.10`
- Git Revision: `0c6f86b60cfba67c20733516957c0a654eb2b44c`
- Release Artefact: `bitbake-0c6f86b60cfba67c20733516957c0a654eb2b44c`
- sha: `4caa94ee4d644017b0cc51b702e330191677f7d179018cbcec8b1793949ebc74`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.10/bitbake-0c6f86b60cfba67c20733516957c0a654eb2b44c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.10/bitbake-0c6f86b60cfba67c20733516957c0a654eb2b44c.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.10`
- Git Revision: `8388be749806bd0bf4fccf1005dae8f643aa4ef4`

## 17.11.13 Release notes for Yocto-4.0.11 (Kirkstone)

### Security Fixes in Yocto-4.0.11

- cups: Fix [CVE-2023-32324](#)
- curl: Fix [CVE-2023-28319](#), [CVE-2023-28320](#), [CVE-2023-28321](#) and [CVE-2023-28322](#)
- git: Ignore [CVE-2023-25815](#)
- go: Fix [CVE-2023-24539](#) and [CVE-2023-24540](#)
- nasm: Fix [CVE-2022-46457](#)
- openssh: Fix [CVE-2023-28531](#)
- openssl: Fix [CVE-2023-1255](#) and [CVE-2023-2650](#)
- perl: Fix [CVE-2023-31484](#)
- python3-requests: Fix for [CVE-2023-32681](#)
- sysstat: Fix [CVE-2023-33204](#)
- vim: Fix [CVE-2023-2426](#)
- webkitgtk: fix [CVE-2022-42867](#), [CVE-2022-46691](#), [CVE-2022-46699](#) and [CVE-2022-46700](#)

### Fixes in Yocto-4.0.11

- Revert "docs: conf.py: fix cve extlinks caption for sphinx <4.0"
- Revert "ipk: Decode byte data to string in manifest handling"
- avahi: fix D-Bus introspection
- build-appliance-image: Update to kirkstone head revision
- conf.py: add macro for Mitre CVE links
- conf: add nice level to the hash config ignored variables
- cpio: Fix wrong CRC with ASCII CRC for large files
- cve-update-nvd2-native: added the missing http import
- cve-update-nvd2-native: new CVE database fetcher
- dhcpcd: use git instead of tarballs
- e2fsprogs: fix ptest bug for second running
- gcc-runtime: Use static dummy libstdc++
- glibc: stable 2.35 branch updates (cbceb903c4d7)
- go.bbclass: don't use test to check output from ls
- gstreamer1.0: Upgrade to 1.20.6
- iso-codes: Upgrade to 4.15.0
- kernel-devicetree: allow specification of dtb directory

- kernel-devicetree: make shell scripts posix compliant
- kernel-devicetree: recursively search for dtbs
- kernel: don't force PAHOLE=false
- kmscube: Correct *DEPENDS* to avoid overwrite
- lib/terminal.py: Add urxvt terminal
- license.bbclass: Include *LICENSE* in the output when it fails to parse
- linux-yocto/5.10: Upgrade to v5.10.180
- linux-yocto/5.15: Upgrade to v5.15.113
- llvm: backport a fix for build with gcc-13
- maintainers.inc: Fix email address typo
- maintainers.inc: Move repo to unassigned
- migration-guides: add release notes for 4.0.10
- migration-guides: use new cve\_mitre macro
- nghttp2: Deleted the entries for -client and -server, and removed a dependency on them from the main package.
- oeqa/selftest/cases/devtool.py: skip all tests require folder a git repo
- openssl: Remove BSD-4-clause contents completely from codebase
- openssl: Upgrade to 3.0.9
- overview-manual: concepts.rst: Fix a typo
- p11-kit: add native to *BBCLASSEXTEND*
- package: enable recursion on file globs
- package\_manager/ipk: fix config path generation in \_create\_custom\_config()
- piglit: Add *PACKAGECONFIG* for glx and opengl
- piglit: Add missing glslang dependencies
- piglit: Fix build time dependency
- poky.conf: bump version for 4.0.11
- profile-manual: fix blktrace remote usage instructions
- quilt: Fix merge.test race condition
- ref-manual: add clarification for *SRCREV*
- selftest/reproducible: Allow native/cross reuse in test
- staging.bbclass: do not add extend\_recipe\_sysroot to prefuns of prepare\_recipe\_sysroot
- systemd-networkd: backport fix for rm unmanaged wifi
- systemd-systemctl: fix instance template WantedBy symlink construction

- systemd-systemctl: support instance expansion in WantedBy
- uninative: Upgrade to 3.10 to support gcc 13
- uninative: Upgrade to 4.0 to include latest gcc 13.1.1
- vim: Upgrade to 9.0.1527
- waffle: Upgrade to 1.7.2
- weston: add xwayland to *DEPENDS* for *PACKAGECONFIG* xwayland

### **Known Issues in Yocto-4.0.11**

- N/A

### **Contributors to Yocto-4.0.11**

- Alexander Kanavin
- Andrew Jeffery
- Archana Polampalli
- Bhabu Bindu
- Bruce Ashfield
- C. Andy Martin
- Chen Qi
- Daniel Ammann
- Deepthi Hemraj
- Ed Beroaset
- Eero Aaltonen
- Enrico Jörns
- Hannu Lounento
- Hitendra Prajapati
- Ian Ray
- Jan Luebbe
- Jan Vermaete
- Khem Raj
- Lee Chee Yang
- Lei Maohui
- Lorenzo Arena
- Marek Vasut
- Marta Rybczynska



- Martin Jansa
- Martin Siegumfeldt
- Michael Halstead
- Michael Opdenacker
- Ming Liu
- Narpat Mali
- Omkar Patil
- Pablo Saavedra
- Pavel Zhukov
- Peter Kjellerstedt
- Peter Marko
- Qiu Tingting
- Quentin Schulz
- Randolph Sapp
- Randy MacLeod
- Ranjitsinh Rathod
- Richard Purdie
- Riyaz Khan
- Sakib Sajal
- Sanjay Chitroda
- Soumya Sambu
- Steve Sakoman
- Thomas Roos
- Tom Hochstein
- Vivek Kumbhar
- Wang Mingyu
- Yogita Urade
- Zoltan Boszormenyi

## Repositories / Downloads for Yocto-4.0.11

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)

- Tag: `yocto-4.0.11`
- Git Revision: `fc697fe87412b9b179ae3a68d266ace85bb1fcc6`
- Release Artefact: `poky-fc697fe87412b9b179ae3a68d266ace85bb1fcc6`
- sha: `d42ab1b76b9d8ab164d86dc0882c908658f6b5be0742b13a71531068f6a5ee98`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.11/poky-fc697fe87412b9b179ae3a68d266ace85bb1fcc6.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.11/poky-fc697fe87412b9b179ae3a68d266ace85bb1fcc6.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.11`
- Git Revision: `7949e786cf8e50f716ff1f1c4797136637205e0c`
- Release Artefact: `oecore-7949e786cf8e50f716ff1f1c4797136637205e0c`
- sha: `3bda3f7d15961bad5490faf3194709528591a97564b5eae3da7345b63be20334`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.11/oecore-7949e786cf8e50f716ff1f1c4797136637205e0c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.11/oecore-7949e786cf8e50f716ff1f1c4797136637205e0c.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.11`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.11/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.11/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.11`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.11/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.11/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.11
- Git Revision: 0c6f86b60cfba67c20733516957c0a654eb2b44c
- Release Artefact: bitbake-0c6f86b60cfba67c20733516957c0a654eb2b44c
- sha: 4caa94ee4d644017b0cc51b702e330191677f7d179018cbcec8b1793949ebc74
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.11/bitbake-0c6f86b60cfba67c20733516957c0a654eb2b44c.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.11/bitbake-0c6f86b60cfba67c20733516957c0a654eb2b44c.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.11
- Git Revision: 6d16d2bde0aa32276a035ee49703e6eea7c7b29a

## 17.11.14 Release notes for Yocto-4.0.12 (Kirkstone)

### Security Fixes in Yocto-4.0.12

- bind: Fix CVE-2023-2828 and CVE-2023-2911
- cups: Fix CVE-2023-34241
- curl: Added CVE-2023-28320 Follow-up patch
- dbus: Fix CVE-2023-34969
- dmidecode: fix CVE-2023-30630
- ghostscript: fix CVE-2023-36664
- go: fix CVE-2023-24531, CVE-2023-24536, CVE-2023-29400, CVE-2023-29402, CVE-2023-29404, CVE-2023-29405 and CVE-2023-29406
- libarchive: Ignore CVE-2023-30571
- libcap: Fix CVE-2023-2602 and CVE-2023-2603
- libjpeg-turbo: Fix CVE-2023-2804
- libpcre2: Fix CVE-2022-41409
- libtiff: fix CVE-2023-26965

- libwebp: Fix [CVE-2023-1999](#)
- libx11: Fix [CVE-2023-3138](#)
- libxpm: Fix [CVE-2022-44617](#)
- ninja: Ignore [CVE-2021-4336](#)
- openssh: Fix [CVE-2023-38408](#)
- openssl: Fix [CVE-2023-2975](#), [CVE-2023-3446](#) and [CVE-2023-3817](#)
- perl: Fix [CVE-2023-31486](#)
- python3: Ignore [CVE-2023-36632](#)
- qemu: Fix [CVE-2023-0330](#), [CVE-2023-2861](#), [CVE-2023-3255](#) and [CVE-2023-3301](#)
- sqlite3: Fix [CVE-2023-36191](#)
- tiff: Fix [CVE-2023-0795](#), [CVE-2023-0796](#), [CVE-2023-0797](#), [CVE-2023-0798](#), [CVE-2023-0799](#), [CVE-2023-25433](#), [CVE-2023-25434](#) and [CVE-2023-25435](#)
- vim: [CVE-2023-2609](#) and [CVE-2023-2610](#)

### Fixes in Yocto-4.0.12

- babeltrace2: Always use BFD linker when building tests with ld-is-ld distro feature
- babeltrace2: upgrade to 2.0.5
- bitbake.conf: add unzstd in *HOSTTOOLS*
- bitbake: bitbake-layers: initialize tinfoil before registering command line arguments
- bitbake: runqueue: Fix deferred task/multiconfig race issue
- blktrace: ask for python3 specifically
- build-appliance-image: Update to kirkstone head revision
- cmake: Fix CMAKE\_SYSTEM\_PROCESSOR setting for SDK
- connman: fix warning by specifying runstatedir at configure time
- cpio: Replace fix wrong CRC with ASCII CRC for large files with upstream backport
- cve-update-nvd2-native: actually use API keys
- cve-update-nvd2-native: always pass str for json.loads()
- cve-update-nvd2-native: fix cvssV3 metrics
- cve-update-nvd2-native: handle all configuration nodes, not just first
- cve-update-nvd2-native: increase retry count
- cve-update-nvd2-native: log a little more
- cve-update-nvd2-native: retry all errors and sleep between retries
- cve-update-nvd2-native: use exact times, don't truncate

- dbus: upgrade to 1.14.8
- devtool: Fix the wrong variable in srcuri\_entry
- diffutils: upgrade to 3.10
- docs: ref-manual: terms: fix typos in *SPDX* term
- fribidi: upgrade to 1.0.13
- gcc: upgrade to v11.4
- gcc-testsuite: Fix ppc cpu specification
- gcc: don't pass --enable-standard-branch-protection
- gcc: fix runpath errors in cc1 binary
- grub: submit determinism.patch upstream
- image\_types: Fix reproducible builds for initramfs and UKI img
- kernel: add missing path to search for debug files
- kmod: remove unused ptest.patch
- layer.conf: Add missing dependency exclusion
- libassuan: upgrade to 2.5.6
- libksba: upgrade to 1.6.4
- libpng: Add ptest for libpng
- libxcrypt: fix build with perl-5.38 and use master branch
- libxcrypt: fix hard-coded ".so" extension
- libxpm: upgrade to 3.5.16
- linux-firmware: upgrade to 20230515
- linux-yocto/5.10: cfg: fix DECNET configuration warning
- linux-yocto/5.10: update to v5.10.185
- linux-yocto/5.15: cfg: fix DECNET configuration warning
- linux-yocto/5.15: update to v5.15.120
- logrotate: Do not create logrotate.status file
- lttnng-ust: upgrade to 2.13.6
- machine/arch-arm64: add -mbranch-protection=standard
- maintainers.inc: correct Carlos Rafael Giani's email address
- maintainers.inc: correct unassigned entries
- maintainers.inc: unassign Adrian Bunk from wireless-regdb
- maintainers.inc: unassign Alistair Francis from opensbi

- maintainers.inc: unassign Andreas Müller from itstool entry
- maintainers.inc: unassign Pascal Bach from cmake entry
- maintainers.inc: unassign Ricardo Neri from ovmf
- maintainers.inc: unassign Richard Weinberger from erofs-utils entry
- mdadm: fix 07revert-inplace ptest
- mdadm: fix segfaults when running ptests
- mdadm: fix util-linux ptest dependency
- mdadm: skip running known broken ptests
- meson.bbclass: Point to llvm-config from native sysroot
- meta: lib: oe: npm\_registry: Add more safe characters
- migration-guides: add release notes for 4.0.11
- minicom: remove unused patch files
- mobile-broadband-provider-info: upgrade to 20230416
- oe-depends-dot: Handle new format for task-depends.dot
- oeqa/runtime/cases/rpm: fix wait\_for\_no\_process\_for\_user failure case
- oeqa/selftest/bbtests: add non-existent prefile/postfile tests
- oeqa/selftest/devtool: add unit test for "devtool add -b"
- openssl: Upgrade to 3.0.10
- openssl: add PERLEXTERNAL path to test its existence
- openssl: use a glob on the PERLEXTERNAL to track updates on the path
- package.bbclass: moving field data process before variable process in process\_pkgconfig
- pm-utils: fix multilib conflictions
- poky.conf: bump version for 4.0.12
- psmisc: Set *ALTERNATIVE* for pstree to resolve conflict with busybox
- pybootchartgui: show elapsed time for each task
- python3: fix missing comma in get\_module\_deps3.py
- python3: upgrade to 3.10.12
- recipetool: Fix inherit in created -native\* recipes
- ref-manual: add LTS and Mixin terms
- ref-manual: document image-specific variant of *INCOMPATIBLE\_LICENSE*
- ref-manual: release-process: update for LTS releases
- rust-llvm: backport a fix for build with gcc-13

- scripts/runqemu: allocate unfsd ports in a way that doesn't race or clash with unrelated processes
- scripts/runqemu: split lock dir creation into a reusable function
- sdk.py: error out when moving file fails
- sdk.py: fix moving dnf contents
- selftest/reproducible.py: support different build targets
- selftest/license: Exclude from world
- selftest/reproducible: Allow chose the package manager
- serf: upgrade to 1.3.10
- strace: Disable failing test
- strace: Merge two similar patches
- strace: Update patches/tests with upstream fixes
- sysfsutils: fetch a supported fork from github
- systemd-systemctl: fix errors in instance name expansion
- systemd: Backport nspawn: make sure host root can write to the uidmapped mounts we prepare for the container payload
- tzdata: upgrade to 2023c
- uboot-extlinux-config.bbclass: fix old override syntax in comment
- unzip: fix configure check for cross compilation
- useradd-staticids.bbclass: improve error message
- util-linux: add alternative links for ipcs,ipcrm
- v86d: Improve kernel dependency
- vim: upgrade to 9.0.1592
- wget: upgrade to 1.21.4
- wic: Add dependencies for erofs-utils
- wireless-regdb: upgrade to 2023.05.03
- xdpinfo: upgrade to 1.3.4
- zip: fix configure check by using \_Static\_assert

### Known Issues in Yocto-4.0.12

- N/A

## **Contributors to Yocto-4.0.12**

- Alberto Planas
- Alexander Kanavin
- Alexander Sverdlin
- Andrej Valek
- Archana Polampalli
- BELOUARGA Mohamed
- Benjamin Bouvier
- Bruce Ashfield
- Charlie Wu
- Chen Qi
- Etienne Cordonnier
- Fabien Mahot
- Frieder Paape
- Frieder Schrempf
- Heiko Thole
- Hitendra Prajapati
- Jermain Horsman
- Jose Quaresma
- Kai Kang
- Khem Raj
- Lee Chee Yang
- Marc Ferland
- Marek Vasut
- Martin Jansa
- Mauro Queiros
- Michael Opdenacker
- Mikko Rapeli
- Nikhil R
- Ovidiu Panait
- Peter Marko
- Poonam Jadhav



- Quentin Schulz
- Richard Purdie
- Ross Burton
- Rusty Howell
- Sakib Sajal
- Soumya Sambu
- Steve Sakoman
- Sundeep KOKKONDA
- Tim Orling
- Tom Hochstein
- Trevor Gamblin
- Vijay Anusuri
- Vivek Kumbhar
- Wang Mingyu
- Xiangyu Chen
- Yoann Congal
- Yogita Urade
- Yuta Hayama

## Repositories / Downloads for Yocto-4.0.12

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.12](#)
- Git Revision: [d6b8790370500b99ca11f0d8a05c39b661ab2ba6](#)
- Release Artefact: [poky-d6b8790370500b99ca11f0d8a05c39b661ab2ba6](#)
- sha: [35f0390e0c5a12f403ed471c0b1254c13cbb9d7c7b46e5a3538e63e36c1ac280](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.12/poky-d6b8790370500b99ca11f0d8a05c39b661ab2ba6.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.12/poky-d6b8790370500b99ca11f0d8a05c39b661ab2ba6.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.12](#)

- Git Revision: [e1a604db8d2cf8782038b4016cc2e2052467333b](#)
- Release Artefact: [oecore-e1a604db8d2cf8782038b4016cc2e2052467333b](#)
- sha: [8b302eb3f3ffe5643f88bc6e4ae8f9a5cda63544d67e04637ecc4197e9750a1d](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.12/oecore-e1a604db8d2cf8782038b4016cc2e2052467333b.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.12/oecore-e1a604db8d2cf8782038b4016cc2e2052467333b.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.12](#)
- Git Revision: [a90614a6498c3345704e9611f2842eb933dc51c1](#)
- Release Artefact: [meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1](#)
- sha: [49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.12/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.12/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.12](#)
- Git Revision: [d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- Release Artefact: [meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- sha: [c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.12/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.12/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.0](#)
- Tag: [yocto-4.0.12](#)
- Git Revision: [41b6684489d0261753344956042be2cc4adb0159](#)
- Release Artefact: [bitbake-41b6684489d0261753344956042be2cc4adb0159](#)
- sha: [efa2b1c4d0be115ed3960750d1e4ed958771b2db6d7baee2d13ad386589376e8](#)

- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.12/bitbake-41b6684489d0261753344956042be2cc4adb0159.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.12/bitbake-41b6684489d0261753344956042be2cc4adb0159.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.12
- Git Revision: 4dfef81ac6164764c6541e39a9fef81d49227096

### 17.11.15 Release notes for Yocto-4.0.13 (Kirkstone)

#### Security Fixes in Yocto-4.0.13

- bind: Fix CVE-2023-2829
- binutils: Fix CVE-2022-48065
- busybox: Fix CVE-2022-48174
- cups: Fix CVE-2023-32360
- curl: Fix CVE-2023-32001
- dmidecode: Fix CVE-2023-30630
- dropbear: Fix CVE-2023-36328
- ffmpeg: Ignored CVE-2023-39018
- file: Fix CVE-2022-48554
- flac: Fix CVE-2020-22219
- gcc: Fix CVE-2023-4039
- gdb: Fix CVE-2023-39128
- ghostscript: Fix CVE-2023-38559
- glib-2.0: Fix CVE-2023-29499, CVE-2023-32611, CVE-2023-32636, CVE-2023-32643 and CVE-2023-32665
- go: Fix CVE-2023-29409 and CVE-2023-39319
- gstreamer1.0-plugins-bad: Fix CVE-2023-37329
- gstreamer1.0-plugins-base: Fix CVE-2023-37328
- gstreamer1.0-plugins-good: Fix CVE-2023-37327
- inetutils: Fix CVE-2023-40303
- json-c: Fix CVE-2021-32292
- libsvg: Fix CVE-2023-38633
- libssh2: Fix CVE-2020-22218

- libtiff: Fix CVE-2023-26966
- libxml2: Fix CVE-2023-39615
- linux-yocto/5.15: Ignore CVE-2003-1604, CVE-2004-0230, CVE-2006-3635, CVE-2006-5331, CVE-2006-6128, CVE-2007-4774, CVE-2007-6761, CVE-2007-6762, CVE-2008-7316, CVE-2009-2692, CVE-2010-0008, CVE-2010-3432, CVE-2010-4648, CVE-2010-5313, CVE-2010-5328, CVE-2010-5329, CVE-2010-5331, CVE-2010-5332, CVE-2011-4098, CVE-2011-4131, CVE-2011-4915, CVE-2011-5321, CVE-2011-5327, CVE-2012-0957, CVE-2012-2119, CVE-2012-2136, CVE-2012-2137, CVE-2012-2313, CVE-2012-2319, CVE-2012-2372, CVE-2012-2375, CVE-2012-2390, CVE-2012-2669, CVE-2012-2744, CVE-2012-2745, CVE-2012-3364, CVE-2012-3375, CVE-2012-3400, CVE-2012-3412, CVE-2012-3430, CVE-2012-3510, CVE-2012-3511, CVE-2012-3520, CVE-2012-3552, CVE-2012-4398, CVE-2012-4444, CVE-2012-4461, CVE-2012-4467, CVE-2012-4508, CVE-2012-4530, CVE-2012-4565, CVE-2012-5374, CVE-2012-5375, CVE-2012-5517, CVE-2012-6536, CVE-2012-6537, CVE-2012-6538, CVE-2012-6539, CVE-2012-6540, CVE-2012-6541, CVE-2012-6542, CVE-2012-6543, CVE-2012-6544, CVE-2012-6545, CVE-2012-6546, CVE-2012-6547, CVE-2012-6548, CVE-2012-6549, CVE-2012-6638, CVE-2012-6647, CVE-2012-6657, CVE-2012-6689, CVE-2012-6701, CVE-2012-6703, CVE-2012-6704, CVE-2012-6712, CVE-2013-0160, CVE-2013-0190, CVE-2013-0216, CVE-2013-0217, CVE-2013-0228, CVE-2013-0231, CVE-2013-0268, CVE-2013-0290, CVE-2013-0309, CVE-2013-0310, CVE-2013-0311, CVE-2013-0313, CVE-2013-0343, CVE-2013-0349, CVE-2013-0871, CVE-2013-0913, CVE-2013-0914, CVE-2013-1059, CVE-2013-1763, CVE-2013-1767, CVE-2013-1772, CVE-2013-1773, CVE-2013-1774, CVE-2013-1792, CVE-2013-1796, CVE-2013-1797, CVE-2013-1798, CVE-2013-1819, CVE-2013-1826, CVE-2013-1827, CVE-2013-1828, CVE-2013-1848, CVE-2013-1858, CVE-2013-1860, CVE-2013-1928, CVE-2013-1929, CVE-2013-1943, CVE-2013-1956, CVE-2013-1957, CVE-2013-1958, CVE-2013-1959, CVE-2013-1979, CVE-2013-2015, CVE-2013-2017, CVE-2013-2058, CVE-2013-2094, CVE-2013-2128, CVE-2013-2140, CVE-2013-2141, CVE-2013-2146, CVE-2013-2147, CVE-2013-2148, CVE-2013-2164, CVE-2013-2206, CVE-2013-2232, CVE-2013-2234, CVE-2013-2237, CVE-2013-2546, CVE-2013-2547, CVE-2013-2548, CVE-2013-2596, CVE-2013-2634, CVE-2013-2635, CVE-2013-2636, CVE-2013-2850, CVE-2013-2851, CVE-2013-2852, CVE-2013-2888, CVE-2013-2889, CVE-2013-2890, CVE-2013-2891, CVE-2013-2892, CVE-2013-2893, CVE-2013-2894, CVE-2013-2895, CVE-2013-2896, CVE-2013-2897, CVE-2013-2898, CVE-2013-2899, CVE-2013-2929, CVE-2013-2930, CVE-2013-3076, CVE-2013-3222, CVE-2013-3223, CVE-2013-3224, CVE-2013-3225, CVE-2013-3226, CVE-2013-3227, CVE-2013-3228, CVE-2013-3229, CVE-2013-3230, CVE-2013-3231, CVE-2013-3232, CVE-2013-3233, CVE-2013-3234, CVE-2013-3235, CVE-2013-3236, CVE-2013-3237, CVE-2013-3301, CVE-2013-3302, CVE-2013-4125, CVE-2013-4127, CVE-2013-4129, CVE-2013-4162, CVE-2013-4163, CVE-2013-4205, CVE-2013-4220, CVE-2013-4247, CVE-2013-4254, CVE-2013-4270, CVE-2013-4299, CVE-2013-4300, CVE-2013-4312, CVE-2013-4343, CVE-2013-4345, CVE-2013-4348, CVE-2013-4350, CVE-2013-4387, CVE-2013-4470, CVE-2013-4483, CVE-2013-4511, CVE-2013-4512, CVE-2013-4513, CVE-2013-4514, CVE-2013-4515, CVE-2013-4516, CVE-2013-4563, CVE-2013-4579, CVE-2013-4587, CVE-2013-4588, CVE-2013-4591, CVE-2013-4592, CVE-2013-5634, CVE-2013-6282, CVE-2013-6367, CVE-2013-6368, CVE-2013-6376, CVE-2013-6378, CVE-2013-6380, CVE-2013-6381, CVE-2013-6382, CVE-2013-6383, CVE-2013-6431, CVE-2013-6432, CVE-2013-6885, CVE-2013-7026, CVE-2013-7027, CVE-2013-7263, CVE-2013-7264, CVE-2013-7265, CVE-2013-7266, CVE-2013-7267, CVE-2013-7268, CVE-2013-7269, CVE-2013-7270, CVE-2013-7271, CVE-2013-7281, CVE-2013-7339, CVE-2013-7348, CVE-2013-7421, CVE-2013-7446, CVE-2013-7470, CVE-2014-0038, CVE-2014-0049, CVE-2014-0055, CVE-2014-0069, CVE-2014-0077, CVE-2014-0100, CVE-2014-0101, CVE-2014-0102, CVE-2014-0131, CVE-2014-0155, CVE-2014-0181, CVE-2014-0196, CVE-2014-

0203, CVE-2014-0205, CVE-2014-0206, CVE-2014-1438, CVE-2014-1444, CVE-2014-1445, CVE-2014-1446, CVE-2014-1690, CVE-2014-1737, CVE-2014-1738, CVE-2014-1739, CVE-2014-1874, CVE-2014-2038, CVE-2014-2039, CVE-2014-2309, CVE-2014-2523, CVE-2014-2568, CVE-2014-2580, CVE-2014-2672, CVE-2014-2673, CVE-2014-2678, CVE-2014-2706, CVE-2014-2739, CVE-2014-2851, CVE-2014-2889, CVE-2014-3122, CVE-2014-3144, CVE-2014-3145, CVE-2014-3153, CVE-2014-3180, CVE-2014-3181, CVE-2014-3182, CVE-2014-3183, CVE-2014-3184, CVE-2014-3185, CVE-2014-3186, CVE-2014-3534, CVE-2014-3535, CVE-2014-3601, CVE-2014-3610, CVE-2014-3611, CVE-2014-3631, CVE-2014-3645, CVE-2014-3646, CVE-2014-3647, CVE-2014-3673, CVE-2014-3687, CVE-2014-3688, CVE-2014-3690, CVE-2014-3917, CVE-2014-3940, CVE-2014-4014, CVE-2014-4027, CVE-2014-4157, CVE-2014-4171, CVE-2014-4508, CVE-2014-4608, CVE-2014-4611, CVE-2014-4652, CVE-2014-4653, CVE-2014-4654, CVE-2014-4655, CVE-2014-4656, CVE-2014-4667, CVE-2014-4699, CVE-2014-4943, CVE-2014-5045, CVE-2014-5077, CVE-2014-5206, CVE-2014-5207, CVE-2014-5471, CVE-2014-5472, CVE-2014-6410, CVE-2014-6416, CVE-2014-6417, CVE-2014-6418, CVE-2014-7145, CVE-2014-7283, CVE-2014-7284, CVE-2014-7822, CVE-2014-7825, CVE-2014-7826, CVE-2014-7841, CVE-2014-7842, CVE-2014-7843, CVE-2014-7970, CVE-2014-7975, CVE-2014-8086, CVE-2014-8133, CVE-2014-8134, CVE-2014-8159, CVE-2014-8160, CVE-2014-8171, CVE-2014-8172, CVE-2014-8173, CVE-2014-8369, CVE-2014-8480, CVE-2014-8481, CVE-2014-8559, CVE-2014-8709, CVE-2014-8884, CVE-2014-8989, CVE-2014-9090, CVE-2014-9322, CVE-2014-9419, CVE-2014-9420, CVE-2014-9428, CVE-2014-9529, CVE-2014-9584, CVE-2014-9585, CVE-2014-9644, CVE-2014-9683, CVE-2014-9710, CVE-2014-9715, CVE-2014-9717, CVE-2014-9728, CVE-2014-9729, CVE-2014-9730, CVE-2014-9731, CVE-2014-9803, CVE-2014-9870, CVE-2014-9888, CVE-2014-9895, CVE-2014-9903, CVE-2014-9904, CVE-2014-9914, CVE-2014-9922, CVE-2014-9940, CVE-2015-0239, CVE-2015-0274, CVE-2015-0275, CVE-2015-1333, CVE-2015-1339, CVE-2015-1350, CVE-2015-1420, CVE-2015-1421, CVE-2015-1465, CVE-2015-1573, CVE-2015-1593, CVE-2015-1805, CVE-2015-2041, CVE-2015-2042, CVE-2015-2150, CVE-2015-2666, CVE-2015-2672, CVE-2015-2686, CVE-2015-2830, CVE-2015-2922, CVE-2015-2925, CVE-2015-3212, CVE-2015-3214, CVE-2015-3288, CVE-2015-3290, CVE-2015-3291, CVE-2015-3331, CVE-2015-3339, CVE-2015-3636, CVE-2015-4001, CVE-2015-4002, CVE-2015-4003, CVE-2015-4004, CVE-2015-4036, CVE-2015-4167, CVE-2015-4170, CVE-2015-4176, CVE-2015-4177, CVE-2015-4178, CVE-2015-4692, CVE-2015-4700, CVE-2015-5156, CVE-2015-5157, CVE-2015-5257, CVE-2015-5283, CVE-2015-5307, CVE-2015-5327, CVE-2015-5364, CVE-2015-5366, CVE-2015-5697, CVE-2015-5706, CVE-2015-5707, CVE-2015-6252, CVE-2015-6526, CVE-2015-6937, CVE-2015-7509, CVE-2015-7513, CVE-2015-7515, CVE-2015-7550, CVE-2015-7566, CVE-2015-7613, CVE-2015-7799, CVE-2015-7833, CVE-2015-7872, CVE-2015-7884, CVE-2015-7885, CVE-2015-7990, CVE-2015-8104, CVE-2015-8215, CVE-2015-8324, CVE-2015-8374, CVE-2015-8539, CVE-2015-8543, CVE-2015-8550, CVE-2015-8551, CVE-2015-8552, CVE-2015-8553, CVE-2015-8569, CVE-2015-8575, CVE-2015-8660, CVE-2015-8709, CVE-2015-8746, CVE-2015-8767, CVE-2015-8785, CVE-2015-8787, CVE-2015-8812, CVE-2015-8816, CVE-2015-8830, CVE-2015-8839, CVE-2015-8844, CVE-2015-8845, CVE-2015-8950, CVE-2015-8952, CVE-2015-8953, CVE-2015-8955, CVE-2015-8956, CVE-2015-8961, CVE-2015-8962, CVE-2015-8963, CVE-2015-8964, CVE-2015-8966, CVE-2015-8967, CVE-2015-8970, CVE-2015-9004, CVE-2015-9016, CVE-2015-9289, CVE-2016-0617, CVE-2016-0723, CVE-2016-0728, CVE-2016-0758, CVE-2016-0821, CVE-2016-0823, CVE-2016-10044, CVE-2016-10088, CVE-2016-10147, CVE-2016-10150, CVE-2016-10153, CVE-2016-10154, CVE-2016-10200, CVE-2016-10208, CVE-2016-10229, CVE-2016-10318, CVE-2016-10723, CVE-2016-10741, CVE-2016-10764, CVE-2016-10905, CVE-2016-10906, CVE-2016-10907, CVE-2016-1237, CVE-2016-1575, CVE-2016-1576, CVE-2016-1583, CVE-2016-2053, CVE-2016-2069, CVE-2016-2070, CVE-2016-2085, CVE-2016-2117, CVE-2016-2143, CVE-2016-2184, CVE-2016-2185, CVE-2016-2186, CVE-

2016-2187, CVE-2016-2188, CVE-2016-2383, CVE-2016-2384, CVE-2016-2543, CVE-2016-2544, CVE-2016-2545, CVE-2016-2546, CVE-2016-2547, CVE-2016-2548, CVE-2016-2549, CVE-2016-2550, CVE-2016-2782, CVE-2016-2847, CVE-2016-3044, CVE-2016-3070, CVE-2016-3134, CVE-2016-3135, CVE-2016-3136, CVE-2016-3137, CVE-2016-3138, CVE-2016-3139, CVE-2016-3140, CVE-2016-3156, CVE-2016-3157, CVE-2016-3672, CVE-2016-3689, CVE-2016-3713, CVE-2016-3841, CVE-2016-3857, CVE-2016-3951, CVE-2016-3955, CVE-2016-3961, CVE-2016-4440, CVE-2016-4470, CVE-2016-4482, CVE-2016-4485, CVE-2016-4486, CVE-2016-4557, CVE-2016-4558, CVE-2016-4565, CVE-2016-4568, CVE-2016-4569, CVE-2016-4578, CVE-2016-4580, CVE-2016-4581, CVE-2016-4794, CVE-2016-4805, CVE-2016-4913, CVE-2016-4951, CVE-2016-4997, CVE-2016-4998, CVE-2016-5195, CVE-2016-5243, CVE-2016-5244, CVE-2016-5400, CVE-2016-5412, CVE-2016-5696, CVE-2016-5728, CVE-2016-5828, CVE-2016-5829, CVE-2016-6130, CVE-2016-6136, CVE-2016-6156, CVE-2016-6162, CVE-2016-6187, CVE-2016-6197, CVE-2016-6198, CVE-2016-6213, CVE-2016-6327, CVE-2016-6480, CVE-2016-6516, CVE-2016-6786, CVE-2016-6787, CVE-2016-6828, CVE-2016-7039, CVE-2016-7042, CVE-2016-7097, CVE-2016-7117, CVE-2016-7425, CVE-2016-7910, CVE-2016-7911, CVE-2016-7912, CVE-2016-7913, CVE-2016-7914, CVE-2016-7915, CVE-2016-7916, CVE-2016-7917, CVE-2016-8399, CVE-2016-8405, CVE-2016-8630, CVE-2016-8632, CVE-2016-8633, CVE-2016-8636, CVE-2016-8645, CVE-2016-8646, CVE-2016-8650, CVE-2016-8655, CVE-2016-8658, CVE-2016-8666, CVE-2016-9083, CVE-2016-9084, CVE-2016-9120, CVE-2016-9178, CVE-2016-9191, CVE-2016-9313, CVE-2016-9555, CVE-2016-9576, CVE-2016-9588, CVE-2016-9604, CVE-2016-9685, CVE-2016-9754, CVE-2016-9755, CVE-2016-9756, CVE-2016-9777, CVE-2016-9793, CVE-2016-9794, CVE-2016-9806, CVE-2016-9919, CVE-2017-0605, CVE-2017-0627, CVE-2017-0750, CVE-2017-0786, CVE-2017-0861, CVE-2017-1000, CVE-2017-1000111, CVE-2017-1000112, CVE-2017-1000251, CVE-2017-1000252, CVE-2017-1000253, CVE-2017-1000255, CVE-2017-1000363, CVE-2017-1000364, CVE-2017-1000365, CVE-2017-1000370, CVE-2017-1000371, CVE-2017-1000379, CVE-2017-1000380, CVE-2017-1000405, CVE-2017-1000407, CVE-2017-1000410, CVE-2017-10661, CVE-2017-10662, CVE-2017-10663, CVE-2017-10810, CVE-2017-10911, CVE-2017-11089, CVE-2017-11176, CVE-2017-11472, CVE-2017-11473, CVE-2017-11600, CVE-2017-12134, CVE-2017-12146, CVE-2017-12153, CVE-2017-12154, CVE-2017-12168, CVE-2017-12188, CVE-2017-12190, CVE-2017-12192, CVE-2017-12193, CVE-2017-12762, CVE-2017-13080, CVE-2017-13166, CVE-2017-13167, CVE-2017-13168, CVE-2017-13215, CVE-2017-13216, CVE-2017-13220, CVE-2017-13305, CVE-2017-13686, CVE-2017-13695, CVE-2017-13715, CVE-2017-14051, CVE-2017-14106, CVE-2017-14140, CVE-2017-14156, CVE-2017-14340, CVE-2017-14489, CVE-2017-14497, CVE-2017-14954, CVE-2017-14991, CVE-2017-15102, CVE-2017-15115, CVE-2017-15116, CVE-2017-15121, CVE-2017-15126, CVE-2017-15127, CVE-2017-15128, CVE-2017-15129, CVE-2017-15265, CVE-2017-15274, CVE-2017-15299, CVE-2017-15306, CVE-2017-15537, CVE-2017-15649, CVE-2017-15868, CVE-2017-15951, CVE-2017-16525, CVE-2017-16526, CVE-2017-16527, CVE-2017-16528, CVE-2017-16529, CVE-2017-16530, CVE-2017-16531, CVE-2017-16532, CVE-2017-16533, CVE-2017-16534, CVE-2017-16535, CVE-2017-16536, CVE-2017-16537, CVE-2017-16538, CVE-2017-16643, CVE-2017-16644, CVE-2017-16645, CVE-2017-16646, CVE-2017-16647, CVE-2017-16648, CVE-2017-16649, CVE-2017-16650, CVE-2017-16911, CVE-2017-16912, CVE-2017-16913, CVE-2017-16914, CVE-2017-16939, CVE-2017-16994, CVE-2017-16995, CVE-2017-16996, CVE-2017-17052, CVE-2017-17053, CVE-2017-17448, CVE-2017-17449, CVE-2017-17450, CVE-2017-17558, CVE-2017-17712, CVE-2017-17741, CVE-2017-17805, CVE-2017-17806, CVE-2017-17807, CVE-2017-17852, CVE-2017-17853, CVE-2017-17854, CVE-2017-17855, CVE-2017-17856, CVE-2017-17857, CVE-2017-17862, CVE-2017-17863, CVE-2017-17864, CVE-2017-17975, CVE-2017-18017, CVE-2017-18075, CVE-2017-18079, CVE-2017-18174, CVE-2017-18193, CVE-2017-18200, CVE-2017-18202, CVE-2017-18203, CVE-2017-

18204, CVE-2017-18208, CVE-2017-18216, CVE-2017-18218, CVE-2017-18221, CVE-2017-18222, CVE-2017-18224, CVE-2017-18232, CVE-2017-18241, CVE-2017-18249, CVE-2017-18255, CVE-2017-18257, CVE-2017-18261, CVE-2017-18270, CVE-2017-18344, CVE-2017-18360, CVE-2017-18379, CVE-2017-18509, CVE-2017-18549, CVE-2017-18550, CVE-2017-18551, CVE-2017-18552, CVE-2017-18595, CVE-2017-2583, CVE-2017-2584, CVE-2017-2596, CVE-2017-2618, CVE-2017-2634, CVE-2017-2636, CVE-2017-2647, CVE-2017-2671, CVE-2017-5123, CVE-2017-5546, CVE-2017-5547, CVE-2017-5548, CVE-2017-5549, CVE-2017-5550, CVE-2017-5551, CVE-2017-5576, CVE-2017-5577, CVE-2017-5669, CVE-2017-5715, CVE-2017-5753, CVE-2017-5754, CVE-2017-5897, CVE-2017-5967, CVE-2017-5970, CVE-2017-5972, CVE-2017-5986, CVE-2017-6001, CVE-2017-6074, CVE-2017-6214, CVE-2017-6345, CVE-2017-6346, CVE-2017-6347, CVE-2017-6348, CVE-2017-6353, CVE-2017-6874, CVE-2017-6951, CVE-2017-7184, CVE-2017-7187, CVE-2017-7261, CVE-2017-7273, CVE-2017-7277, CVE-2017-7294, CVE-2017-7308, CVE-2017-7346, CVE-2017-7374, CVE-2017-7472, CVE-2017-7477, CVE-2017-7482, CVE-2017-7487, CVE-2017-7495, CVE-2017-7518, CVE-2017-7533, CVE-2017-7541, CVE-2017-7542, CVE-2017-7558, CVE-2017-7616, CVE-2017-7618, CVE-2017-7645, CVE-2017-7889, CVE-2017-7895, CVE-2017-7979, CVE-2017-8061, CVE-2017-8062, CVE-2017-8063, CVE-2017-8064, CVE-2017-8065, CVE-2017-8066, CVE-2017-8067, CVE-2017-8068, CVE-2017-8069, CVE-2017-8070, CVE-2017-8071, CVE-2017-8072, CVE-2017-8106, CVE-2017-8240, CVE-2017-8797, CVE-2017-8824, CVE-2017-8831, CVE-2017-8890, CVE-2017-8924, CVE-2017-8925, CVE-2017-9059, CVE-2017-9074, CVE-2017-9075, CVE-2017-9076, CVE-2017-9077, CVE-2017-9150, CVE-2017-9211, CVE-2017-9242, CVE-2017-9605, CVE-2017-9725, CVE-2017-9984, CVE-2017-9985, CVE-2017-9986, CVE-2018-1000004, CVE-2018-1000026, CVE-2018-1000028, CVE-2018-1000199, CVE-2018-1000200, CVE-2018-1000204, CVE-2018-10021, CVE-2018-10074, CVE-2018-10087, CVE-2018-10124, CVE-2018-10322, CVE-2018-10323, CVE-2018-1065, CVE-2018-1066, CVE-2018-10675, CVE-2018-1068, CVE-2018-10840, CVE-2018-10853, CVE-2018-1087, CVE-2018-10876, CVE-2018-10877, CVE-2018-10878, CVE-2018-10879, CVE-2018-10880, CVE-2018-10881, CVE-2018-10882, CVE-2018-10883, CVE-2018-10901, CVE-2018-10902, CVE-2018-1091, CVE-2018-1092, CVE-2018-1093, CVE-2018-10938, CVE-2018-1094, CVE-2018-10940, CVE-2018-1095, CVE-2018-1108, CVE-2018-1118, CVE-2018-1120, CVE-2018-11232, CVE-2018-1128, CVE-2018-1129, CVE-2018-1130, CVE-2018-11412, CVE-2018-11506, CVE-2018-11508, CVE-2018-12126, CVE-2018-12127, CVE-2018-12130, CVE-2018-12207, CVE-2018-12232, CVE-2018-12233, CVE-2018-12633, CVE-2018-12714, CVE-2018-12896, CVE-2018-12904, CVE-2018-13053, CVE-2018-13093, CVE-2018-13094, CVE-2018-13095, CVE-2018-13096, CVE-2018-13097, CVE-2018-13098, CVE-2018-13099, CVE-2018-13100, CVE-2018-13405, CVE-2018-13406, CVE-2018-14609, CVE-2018-14610, CVE-2018-14611, CVE-2018-14612, CVE-2018-14613, CVE-2018-14614, CVE-2018-14615, CVE-2018-14616, CVE-2018-14617, CVE-2018-14619, CVE-2018-14625, CVE-2018-14633, CVE-2018-14634, CVE-2018-14641, CVE-2018-14646, CVE-2018-14656, CVE-2018-14678, CVE-2018-14734, CVE-2018-15471, CVE-2018-15572, CVE-2018-15594, CVE-2018-16276, CVE-2018-16597, CVE-2018-16658, CVE-2018-16862, CVE-2018-16871, CVE-2018-16880, CVE-2018-16882, CVE-2018-16884, CVE-2018-17182, CVE-2018-17972, CVE-2018-18021, CVE-2018-18281, CVE-2018-18386, CVE-2018-18397, CVE-2018-18445, CVE-2018-18559, CVE-2018-18690, CVE-2018-18710, CVE-2018-18955, CVE-2018-19406, CVE-2018-19407, CVE-2018-19824, CVE-2018-19854, CVE-2018-19985, CVE-2018-20169, CVE-2018-20449, CVE-2018-20509, CVE-2018-20510, CVE-2018-20511, CVE-2018-20669, CVE-2018-20784, CVE-2018-20836, CVE-2018-20854, CVE-2018-20855, CVE-2018-20856, CVE-2018-20961, CVE-2018-20976, CVE-2018-21008, CVE-2018-25015, CVE-2018-25020, CVE-2018-3620, CVE-2018-3639, CVE-2018-3646, CVE-2018-3665, CVE-2018-3693, CVE-2018-5332, CVE-2018-5333, CVE-2018-5344, CVE-2018-5390, CVE-2018-5391, CVE-2018-5703, CVE-2018-5750,



CVE-2018-5803, CVE-2018-5814, CVE-2018-5848, CVE-2018-5873, CVE-2018-5953, CVE-2018-5995, CVE-2018-6412, CVE-2018-6554, CVE-2018-6555, CVE-2018-6927, CVE-2018-7191, CVE-2018-7273, CVE-2018-7480, CVE-2018-7492, CVE-2018-7566, CVE-2018-7740, CVE-2018-7754, CVE-2018-7755, CVE-2018-7757, CVE-2018-7995, CVE-2018-8043, CVE-2018-8087, CVE-2018-8781, CVE-2018-8822, CVE-2018-8897, CVE-2018-9363, CVE-2018-9385, CVE-2018-9415, CVE-2018-9422, CVE-2018-9465, CVE-2018-9516, CVE-2018-9517, CVE-2018-9518, CVE-2018-9568, CVE-2019-0136, CVE-2019-0145, CVE-2019-0146, CVE-2019-0147, CVE-2019-0148, CVE-2019-0149, CVE-2019-0154, CVE-2019-0155, CVE-2019-10124, CVE-2019-10125, CVE-2019-10126, CVE-2019-10142, CVE-2019-10207, CVE-2019-10220, CVE-2019-10638, CVE-2019-10639, CVE-2019-11085, CVE-2019-11091, CVE-2019-11135, CVE-2019-11190, CVE-2019-11191, CVE-2019-1125, CVE-2019-11477, CVE-2019-11478, CVE-2019-11479, CVE-2019-11486, CVE-2019-11487, CVE-2019-11599, CVE-2019-11683, CVE-2019-11810, CVE-2019-11811, CVE-2019-11815, CVE-2019-11833, CVE-2019-11884, CVE-2019-12378, CVE-2019-12379, CVE-2019-12380, CVE-2019-12381, CVE-2019-12382, CVE-2019-12454, CVE-2019-12455, CVE-2019-12614, CVE-2019-12615, CVE-2019-12817, CVE-2019-12818, CVE-2019-12819, CVE-2019-12881, CVE-2019-12984, CVE-2019-13233, CVE-2019-13272, CVE-2019-13631, CVE-2019-13648, CVE-2019-14283, CVE-2019-14284, CVE-2019-14615, CVE-2019-14763, CVE-2019-14814, CVE-2019-14815, CVE-2019-14816, CVE-2019-14821, CVE-2019-14835, CVE-2019-14895, CVE-2019-14896, CVE-2019-14897, CVE-2019-14901, CVE-2019-15030, CVE-2019-15031, CVE-2019-15090, CVE-2019-15098, CVE-2019-15099, CVE-2019-15117, CVE-2019-15118, CVE-2019-15211, CVE-2019-15212, CVE-2019-15213, CVE-2019-15214, CVE-2019-15215, CVE-2019-15216, CVE-2019-15217, CVE-2019-15218, CVE-2019-15219, CVE-2019-15220, CVE-2019-15221, CVE-2019-15222, CVE-2019-15223, CVE-2019-15291, CVE-2019-15292, CVE-2019-15504, CVE-2019-15505, CVE-2019-15538, CVE-2019-15666, CVE-2019-15794, CVE-2019-15807, CVE-2019-15916, CVE-2019-15917, CVE-2019-15918, CVE-2019-15919, CVE-2019-15920, CVE-2019-15921, CVE-2019-15922, CVE-2019-15923, CVE-2019-15924, CVE-2019-15925, CVE-2019-15926, CVE-2019-15927, CVE-2019-16229, CVE-2019-16230, CVE-2019-16231, CVE-2019-16232, CVE-2019-16233, CVE-2019-16234, CVE-2019-16413, CVE-2019-16714, CVE-2019-16746, CVE-2019-16921, CVE-2019-16994, CVE-2019-16995, CVE-2019-17052, CVE-2019-17053, CVE-2019-17054, CVE-2019-17055, CVE-2019-17056, CVE-2019-17075, CVE-2019-17133, CVE-2019-17351, CVE-2019-17666, CVE-2019-18198, CVE-2019-18282, CVE-2019-18660, CVE-2019-18675, CVE-2019-18683, CVE-2019-18786, CVE-2019-18805, CVE-2019-18806, CVE-2019-18807, CVE-2019-18808, CVE-2019-18809, CVE-2019-18810, CVE-2019-18811, CVE-2019-18812, CVE-2019-18813, CVE-2019-18814, CVE-2019-18885, CVE-2019-19036, CVE-2019-19037, CVE-2019-19039, CVE-2019-19043, CVE-2019-19044, CVE-2019-19045, CVE-2019-19046, CVE-2019-19047, CVE-2019-19048, CVE-2019-19049, CVE-2019-19050, CVE-2019-19051, CVE-2019-19052, CVE-2019-19053, CVE-2019-19054, CVE-2019-19055, CVE-2019-19056, CVE-2019-19057, CVE-2019-19058, CVE-2019-19059, CVE-2019-19060, CVE-2019-19061, CVE-2019-19062, CVE-2019-19063, CVE-2019-19064, CVE-2019-19065, CVE-2019-19066, CVE-2019-19067, CVE-2019-19068, CVE-2019-19069, CVE-2019-19070, CVE-2019-19071, CVE-2019-19072, CVE-2019-19073, CVE-2019-19074, CVE-2019-19075, CVE-2019-19076, CVE-2019-19077, CVE-2019-19078, CVE-2019-19079, CVE-2019-19080, CVE-2019-19081, CVE-2019-19082, CVE-2019-19083, CVE-2019-19227, CVE-2019-19241, CVE-2019-19252, CVE-2019-19318, CVE-2019-19319, CVE-2019-19332, CVE-2019-19338, CVE-2019-19377, CVE-2019-19447, CVE-2019-19448, CVE-2019-19449, CVE-2019-19462, CVE-2019-19523, CVE-2019-19524, CVE-2019-19525, CVE-2019-19526, CVE-2019-19527, CVE-2019-19528, CVE-2019-19529, CVE-2019-19530, CVE-2019-19531, CVE-2019-19532, CVE-2019-19533, CVE-2019-19534, CVE-2019-19535, CVE-2019-19536, CVE-2019-19537, CVE-2019-19543, CVE-2019-19602, CVE-2019-19767,



CVE-2019-19768, CVE-2019-19769, CVE-2019-19770, CVE-2019-19807, CVE-2019-19813, CVE-2019-19815, CVE-2019-19816, CVE-2019-19922, CVE-2019-19927, CVE-2019-19947, CVE-2019-19965 and CVE-2019-1999

- nasm: Fix CVE-2020-21528
- ncurses: Fix CVE-2023-29491
- nhttp2: Fix CVE-2023-35945
- procps: Fix CVE-2023-4016
- python3-certifi: Fix CVE-2023-37920
- python3-git: Fix CVE-2022-24439 and CVE-2023-40267
- python3-pygments: Fix CVE-2022-40896
- python3: Fix CVE-2023-40217
- qemu: Fix CVE-2020-14394, CVE-2021-3638, CVE-2023-2861, CVE-2023-3180 and CVE-2023-3354
- tiff: fix CVE-2023-2908, CVE-2023-3316 and CVE-2023-3618
- vim: Fix CVE-2023-3896, CVE-2023-4733, CVE-2023-4734, CVE-2023-4735, CVE-2023-4736, CVE-2023-4738, CVE-2023-4750 and CVE-2023-4752
- webkitgtk: fix CVE-2022-48503 and CVE-2023-23529

### Fixes in Yocto-4.0.13

- acl/attr: ptest fixes and improvements
- automake: fix buildtest patch
- bind: Upgrade to 9.18.17
- binutils: stable 2.38 branch updates
- build-appliance-image: Update to kirkstone head revision
- build-sysroots: Add *SUMMARY* field
- cargo.bbclass: set up cargo environment in common do\_compile
- contributor-guide: recipe-style-guide: add Upstream-Status
- dbus: Specify runstatedir configure option
- dev-manual: common-tasks: mention faster "find" command to trim sstate cache
- dev-manual: disk-space: improve wording for obsolete sstate cache files
- dev-manual: licenses: mention *SPDX* for license compliance
- dev-manual: licenses: update license manifest location
- dev-manual: new-recipe.rst fix inconsistency with contributor guide
- dev-manual: split common-tasks.rst
- dev-manual: wic.rst: Update native tools build command

- documentation/README: align with master
- efivar: backport 5 patches to fix build with gold
- externalsrc: fix dependency chain issues
- glibc-locale: use stricter matching for metapackages' runtime dependencies
- glibc/check-test-wrapper: don't emit warnings from ssh
- glibc: stable 2.35 branch updates
- gst-devtools: Upgrade to 1.20.7
- gstreamer1.0-libav: Upgrade to 1.20.7
- gstreamer1.0-omx: Upgrade to 1.20.7
- gstreamer1.0-plugins-bad: Upgrade to 1.20.7
- gstreamer1.0-plugins-base: Upgrade to 1.20.7
- gstreamer1.0-plugins-good: Upgrade to 1.20.7
- gstreamer1.0-plugins-ugly: Upgrade to 1.20.7
- gstreamer1.0-python: Upgrade to 1.20.7
- gstreamer1.0-rtsp-server: Upgrade to 1.20.7
- gstreamer1.0-vaapi: Upgrade to 1.20.7
- gstreamer1.0: Upgrade to 1.20.7
- kernel: Fix path comparison in kernel staging dir symlinking
- lib/package\_manager: Improve repo artefact filtering
- libdnf: resolve cstdint inclusion for newer gcc versions
- libnss-nis: Upgrade to 3.2
- librsvg: Upgrade to 2.52.10
- libxcrypt: update *PV* to match *SRCREV*
- linux-firmware : Add firmware of RTL8822 serie
- linux-firmware: Fix mediatek mt7601u firmware path
- linux-firmware: package firmware for Dragonboard 410c
- linux-firmware: split platform-specific Adreno shaders to separate packages
- linux-firmware: Upgrade to 20230625
- linux-yocto/5.10: update to v5.10.188
- linux-yocto/5.15: update to v5.15.124
- linux-yocto: add script to generate kernel *CVE\_CHECK\_IGNORE* entries
- linux/cve-exclusion: add generated CVE\_CHECK\_IGNORES.

- linux/cve-exclusion: remove obsolete manual entries
- manuals: add new contributor guide
- manuals: document "mime-xdg" class and *MIME\_XDG\_PACKAGES*
- manuals: update former references to dev-manual/common-tasks
- mdadm: add util-linux-blockdev ptest dependency
- migration-guides: add release notes for 4.0.12
- npm.bbclass: avoid DeprecationWarning with new python
- oeqa/runtime/ltp: Increase ltp test output timeout
- oeqa/ssh: Further improve process exit handling
- oeqa/target/ssh: Ensure EAGAIN doesn't truncate output
- oeqa/utls/nfs: allow requesting non-udp ports
- pixman: Remove duplication of license MIT
- poky.conf: bump version for 4.0.13
- poky.conf: update *SANITY\_TESTED\_DISTROS* to match autobuilder
- pseudo: Fix to work with glibc 2.38
- python3-git: Upgrade to 3.1.32
- python3: upgrade to 3.10.13
- ref-manual: add Initramfs term
- ref-manual: add meson class and variables
- ref-manual: add new variables
- ref-manual: qa-checks: align with master
- ref-manual: system-requirements: update supported distros
- resulttool/report: Avoid divide by zero
- resulttool/resultutils: allow index generation despite corrupt json
- rootfs: Add debugfs package db file copy and cleanup
- rpm2cpio.sh: update to the last 4.x version
- rpm: Pick debugfs package db files/dirs explicitly
- scripts/create-pull-request: update URLs to git repositories
- scripts/rpm2cpio.sh: Use bzip2 instead of bunzip2
- sdk-manual: extensible.rst: align with master branch
- selftest/cases/glibc.py: fix the override syntax
- selftest/cases/glibc.py: increase the memory for testing

- selftest/cases/glibc.py: switch to using NFS over TCP
- shadow-sysroot: add license information
- sysklogd: fix integration with systemd-journald
- tar: Upgrade to 1.35
- target/ssh: Ensure exit code set for commands
- tcl: prevent installing another copy of tzdata
- template: fix typo in section header
- vim: Upgrade to 9.0.1894
- vim: update obsolete comment
- wic: fix wrong attempt to create file system in unpartitioned regions
- yocto-uninative: Update to 4.2 for glibc 2.38
- yocto-uninative: Update to 4.3

### **Known Issues in Yocto-4.0.13**

- N/A

### **Contributors to Yocto-4.0.13**

- Abe Kohandel
- Adrian Freihofer
- Alberto Planas
- Alex Kiernan
- Alexander Kanavin
- Alexis Lothoré
- Anuj Mittal
- Archana Polampalli
- Ashish Sharma
- BELOUARGA Mohamed
- Bruce Ashfield
- Changqing Li
- Dmitry Baryshkov
- Enrico Scholz
- Etienne Cordonnier
- Hitendra Prajapati
- Julien Stephan

- Kai Kang
- Khem Raj
- Lee Chee Yang
- Marek Vasut
- Markus Niebel
- Martin Jansa
- Meenali Gupta
- Michael Halstead
- Michael Opdenacker
- Narpat Mali
- Ovidiu Panait
- Pavel Zhukov
- Peter Marko
- Peter Suti
- Poonam Jadhav
- Richard Purdie
- Roland Hieber
- Ross Burton
- Sanjana
- Siddharth Doshi
- Soumya Sambu
- Staffan Rydén
- Steve Sakoman
- Trevor Gamblin
- Vijay Anusuri
- Vivek Kumbhar
- Wang Mingyu
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.13

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)

- Tag: `yocto-4.0.13`
- Git Revision: `e51bf557f596c4da38789a948a3228ba11455e3c`
- Release Artefact: `poky-e51bf557f596c4da38789a948a3228ba11455e3c`
- sha: `afddadb367a90154751f04993077bceffdc1413f9ba9b8c03acb487d0437286e`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.13/poky-e51bf557f596c4da38789a948a3228ba11455e3c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.13/poky-e51bf557f596c4da38789a948a3228ba11455e3c.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.13`
- Git Revision: `d90e4d5e3cca9cffe8f60841afc63667a9ac39fa`
- Release Artefact: `oecore-d90e4d5e3cca9cffe8f60841afc63667a9ac39fa`
- sha: `56e3bdac81b3628e74dfef2132a54be4db7d87373139a00ed64f5c9a354d716a`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.13/oecore-d90e4d5e3cca9cffe8f60841afc63667a9ac39fa.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.13/oecore-d90e4d5e3cca9cffe8f60841afc63667a9ac39fa.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.13`
- Git Revision: `a90614a6498c3345704e9611f2842eb933dc51c1`
- Release Artefact: `meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1`
- sha: `49f9900bfbbc1c68136f8115b314e95d0b7f6be75edf36a75d9bcd1cca7c6302`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.13/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.13/meta-mingw-a90614a6498c3345704e9611f2842eb933dc51c1.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.13`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.13/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.13/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.13
- Git Revision: 41b6684489d0261753344956042be2cc4adb0159
- Release Artefact: bitbake-41b6684489d0261753344956042be2cc4adb0159
- sha: efa2b1c4d0be115ed3960750d1e4ed958771b2db6d7baee2d13ad386589376e8
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.13/bitbake-41b6684489d0261753344956042be2cc4adb0159.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.13/bitbake-41b6684489d0261753344956042be2cc4adb0159.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.13
- Git Revision: 8f02741de867125f11a37822b2d206be180d4ee3

## 17.11.16 Release notes for Yocto-4.0.14 (Kirkstone)

### Security Fixes in Yocto-4.0.14

- bind: Fix CVE-2023-3341 and CVE-2023-4236
- binutils: Fix CVE-2022-44840, CVE-2022-45703, CVE-2022-47008, CVE-2022-47011, CVE-2022-47673, CVE-2022-47695, CVE-2022-47696 and CVE-2022-48063
- cups: Fix CVE-2023-4504
- curl: Fix CVE-2023-38545 and CVE-2023-38546
- gawk: Fix CVE-2023-4156
- ghostscript: Fix CVE-2023-43115
- glibc: Fix CVE-2023-4806, CVE-2023-4813, CVE-2023-4911 and CVE-2023-5156
- glibc: Ignore CVE-2023-4527
- go: Fix CVE-2023-24538 and CVE-2023-39318
- gstreamer1.0-plugins-bad: fix CVE-2023-40474, CVE-2023-40475 and CVE-2023-40476
- libtiff: Fix CVE-2022-40090 and CVE-2023-1916
- libwebp: Fix CVE-2023-5129

- libx11: Fix CVE-2023-43785, CVE-2023-43786 and CVE-2023-43787
- libxml2: Fix CVE-2023-45322
- libxpm: Fix CVE-2023-43788 and CVE-2023-43789
- linux-firmware: Fix CVE-2022-40982, CVE-2023-20569 and CVE-2023-20593
- linux-yocto: update CVE exclusions
- linux-yocto/5.10: Ignore CVE-2003-1604, CVE-2004-0230, CVE-2006-3635, CVE-2006-5331, CVE-2006-6128, CVE-2007-4774, CVE-2007-6761, CVE-2007-6762, CVE-2008-7316, CVE-2009-2692, CVE-2010-0008, CVE-2010-3432, CVE-2010-4648, CVE-2010-5313, CVE-2010-5328, CVE-2010-5329, CVE-2010-5331, CVE-2010-5332, CVE-2011-4098, CVE-2011-4131, CVE-2011-4915, CVE-2011-5321, CVE-2011-5327, CVE-2012-0957, CVE-2012-2119, CVE-2012-2136, CVE-2012-2137, CVE-2012-2313, CVE-2012-2319, CVE-2012-2372, CVE-2012-2375, CVE-2012-2390, CVE-2012-2669, CVE-2012-2744, CVE-2012-2745, CVE-2012-3364, CVE-2012-3375, CVE-2012-3400, CVE-2012-3412, CVE-2012-3430, CVE-2012-3510, CVE-2012-3511, CVE-2012-3520, CVE-2012-3552, CVE-2012-4398, CVE-2012-4444, CVE-2012-4461, CVE-2012-4467, CVE-2012-4508, CVE-2012-4530, CVE-2012-4565, CVE-2012-5374, CVE-2012-5375, CVE-2012-5517, CVE-2012-6536, CVE-2012-6537, CVE-2012-6538, CVE-2012-6539, CVE-2012-6540, CVE-2012-6541, CVE-2012-6542, CVE-2012-6543, CVE-2012-6544, CVE-2012-6545, CVE-2012-6546, CVE-2012-6547, CVE-2012-6548, CVE-2012-6549, CVE-2012-6638, CVE-2012-6647, CVE-2012-6657, CVE-2012-6689, CVE-2012-6701, CVE-2012-6703, CVE-2012-6704, CVE-2012-6712, CVE-2013-0160, CVE-2013-0190, CVE-2013-0216, CVE-2013-0217, CVE-2013-0228, CVE-2013-0231, CVE-2013-0268, CVE-2013-0290, CVE-2013-0309, CVE-2013-0310, CVE-2013-0311, CVE-2013-0313, CVE-2013-0343, CVE-2013-0349, CVE-2013-0871, CVE-2013-0913, CVE-2013-0914, CVE-2013-1059, CVE-2013-1763, CVE-2013-1767, CVE-2013-1772, CVE-2013-1773, CVE-2013-1774, CVE-2013-1792, CVE-2013-1796, CVE-2013-1797, CVE-2013-1798, CVE-2013-1819, CVE-2013-1826, CVE-2013-1827, CVE-2013-1828, CVE-2013-1848, CVE-2013-1858, CVE-2013-1860, CVE-2013-1928, CVE-2013-1929, CVE-2013-1943, CVE-2013-1956, CVE-2013-1957, CVE-2013-1958, CVE-2013-1959, CVE-2013-1979, CVE-2013-2015, CVE-2013-2017, CVE-2013-2058, CVE-2013-2094, CVE-2013-2128, CVE-2013-2140, CVE-2013-2141, CVE-2013-2146, CVE-2013-2147, CVE-2013-2148, CVE-2013-2164, CVE-2013-2206, CVE-2013-2232, CVE-2013-2234, CVE-2013-2237, CVE-2013-2546, CVE-2013-2547, CVE-2013-2548, CVE-2013-2596, CVE-2013-2634, CVE-2013-2635, CVE-2013-2636, CVE-2013-2850, CVE-2013-2851, CVE-2013-2852, CVE-2013-2888, CVE-2013-2889, CVE-2013-2890, CVE-2013-2891, CVE-2013-2892, CVE-2013-2893, CVE-2013-2894, CVE-2013-2895, CVE-2013-2896, CVE-2013-2897, CVE-2013-2898, CVE-2013-2899, CVE-2013-2929, CVE-2013-2930, CVE-2013-3076, CVE-2013-3222, CVE-2013-3223, CVE-2013-3224, CVE-2013-3225, CVE-2013-3226, CVE-2013-3227, CVE-2013-3228, CVE-2013-3229, CVE-2013-3230, CVE-2013-3231, CVE-2013-3232, CVE-2013-3233, CVE-2013-3234, CVE-2013-3235, CVE-2013-3236, CVE-2013-3237, CVE-2013-3301, CVE-2013-3302, CVE-2013-4125, CVE-2013-4127, CVE-2013-4129, CVE-2013-4162, CVE-2013-4163, CVE-2013-4205, CVE-2013-4220, CVE-2013-4247, CVE-2013-4254, CVE-2013-4270, CVE-2013-4299, CVE-2013-4300, CVE-2013-4312, CVE-2013-4343, CVE-2013-4345, CVE-2013-4348, CVE-2013-4350, CVE-2013-4387, CVE-2013-4470, CVE-2013-4483, CVE-2013-4511, CVE-2013-4512, CVE-2013-4513, CVE-2013-4514, CVE-2013-4515, CVE-2013-4516, CVE-2013-4563, CVE-2013-4579, CVE-2013-4587, CVE-2013-4588, CVE-2013-4591, CVE-2013-4592, CVE-2013-5634, CVE-2013-6282, CVE-2013-6367, CVE-2013-6368, CVE-2013-6376, CVE-2013-6378, CVE-2013-6380, CVE-2013-6381, CVE-2013-6382, CVE-2013-6383, CVE-2013-6431, CVE-2013-6432, CVE-2013-6885, CVE-2013-7026, CVE-2013-7027, CVE-2013-7263, CVE-2013-7264, CVE-2013-7265, CVE-2013-



7266, CVE-2013-7267, CVE-2013-7268, CVE-2013-7269, CVE-2013-7270, CVE-2013-7271, CVE-2013-7281, CVE-2013-7339, CVE-2013-7348, CVE-2013-7421, CVE-2013-7446, CVE-2013-7470, CVE-2014-0038, CVE-2014-0049, CVE-2014-0055, CVE-2014-0069, CVE-2014-0077, CVE-2014-0100, CVE-2014-0101, CVE-2014-0102, CVE-2014-0131, CVE-2014-0155, CVE-2014-0181, CVE-2014-0196, CVE-2014-0203, CVE-2014-0205, CVE-2014-0206, CVE-2014-1438, CVE-2014-1444, CVE-2014-1445, CVE-2014-1446, CVE-2014-1690, CVE-2014-1737, CVE-2014-1738, CVE-2014-1739, CVE-2014-1874, CVE-2014-2038, CVE-2014-2039, CVE-2014-2309, CVE-2014-2523, CVE-2014-2568, CVE-2014-2580, CVE-2014-2672, CVE-2014-2673, CVE-2014-2678, CVE-2014-2706, CVE-2014-2739, CVE-2014-2851, CVE-2014-2889, CVE-2014-3122, CVE-2014-3144, CVE-2014-3145, CVE-2014-3153, CVE-2014-3180, CVE-2014-3181, CVE-2014-3182, CVE-2014-3183, CVE-2014-3184, CVE-2014-3185, CVE-2014-3186, CVE-2014-3534, CVE-2014-3535, CVE-2014-3601, CVE-2014-3610, CVE-2014-3611, CVE-2014-3631, CVE-2014-3645, CVE-2014-3646, CVE-2014-3647, CVE-2014-3673, CVE-2014-3687, CVE-2014-3688, CVE-2014-3690, CVE-2014-3917, CVE-2014-3940, CVE-2014-4014, CVE-2014-4027, CVE-2014-4157, CVE-2014-4171, CVE-2014-4508, CVE-2014-4608, CVE-2014-4611, CVE-2014-4652, CVE-2014-4653, CVE-2014-4654, CVE-2014-4655, CVE-2014-4656, CVE-2014-4667, CVE-2014-4699, CVE-2014-4943, CVE-2014-5045, CVE-2014-5077, CVE-2014-5206, CVE-2014-5207, CVE-2014-5471, CVE-2014-5472, CVE-2014-6410, CVE-2014-6416, CVE-2014-6417, CVE-2014-6418, CVE-2014-7145, CVE-2014-7283, CVE-2014-7284, CVE-2014-7822, CVE-2014-7825, CVE-2014-7826, CVE-2014-7841, CVE-2014-7842, CVE-2014-7843, CVE-2014-7970, CVE-2014-7975, CVE-2014-8086, CVE-2014-8133, CVE-2014-8134, CVE-2014-8159, CVE-2014-8160, CVE-2014-8171, CVE-2014-8172, CVE-2014-8173, CVE-2014-8369, CVE-2014-8480, CVE-2014-8481, CVE-2014-8559, CVE-2014-8709, CVE-2014-8884, CVE-2014-8989, CVE-2014-9090, CVE-2014-9322, CVE-2014-9419, CVE-2014-9420, CVE-2014-9428, CVE-2014-9529, CVE-2014-9584, CVE-2014-9585, CVE-2014-9644, CVE-2014-9683, CVE-2014-9710, CVE-2014-9715, CVE-2014-9717, CVE-2014-9728, CVE-2014-9729, CVE-2014-9730, CVE-2014-9731, CVE-2014-9803, CVE-2014-9870, CVE-2014-9888, CVE-2014-9895, CVE-2014-9903, CVE-2014-9904, CVE-2014-9914, CVE-2014-9922, CVE-2014-9940, CVE-2015-0239, CVE-2015-0274, CVE-2015-0275, CVE-2015-1333, CVE-2015-1339, CVE-2015-1350, CVE-2015-1420, CVE-2015-1421, CVE-2015-1465, CVE-2015-1573, CVE-2015-1593, CVE-2015-1805, CVE-2015-2041, CVE-2015-2042, CVE-2015-2150, CVE-2015-2666, CVE-2015-2672, CVE-2015-2686, CVE-2015-2830, CVE-2015-2922, CVE-2015-2925, CVE-2015-3212, CVE-2015-3214, CVE-2015-3288, CVE-2015-3290, CVE-2015-3291, CVE-2015-3331, CVE-2015-3339, CVE-2015-3636, CVE-2015-4001, CVE-2015-4002, CVE-2015-4003, CVE-2015-4004, CVE-2015-4036, CVE-2015-4167, CVE-2015-4170, CVE-2015-4176, CVE-2015-4177, CVE-2015-4178, CVE-2015-4692, CVE-2015-4700, CVE-2015-5156, CVE-2015-5157, CVE-2015-5257, CVE-2015-5283, CVE-2015-5307, CVE-2015-5327, CVE-2015-5364, CVE-2015-5366, CVE-2015-5697, CVE-2015-5706, CVE-2015-5707, CVE-2015-6252, CVE-2015-6526, CVE-2015-6937, CVE-2015-7509, CVE-2015-7513, CVE-2015-7515, CVE-2015-7550, CVE-2015-7566, CVE-2015-7613, CVE-2015-7799, CVE-2015-7833, CVE-2015-7872, CVE-2015-7884, CVE-2015-7885, CVE-2015-7990, CVE-2015-8104, CVE-2015-8215, CVE-2015-8324, CVE-2015-8374, CVE-2015-8539, CVE-2015-8543, CVE-2015-8550, CVE-2015-8551, CVE-2015-8552, CVE-2015-8553, CVE-2015-8569, CVE-2015-8575, CVE-2015-8660, CVE-2015-8709, CVE-2015-8746, CVE-2015-8767, CVE-2015-8785, CVE-2015-8787, CVE-2015-8812, CVE-2015-8816, CVE-2015-8830, CVE-2015-8839, CVE-2015-8844, CVE-2015-8845, CVE-2015-8950, CVE-2015-8952, CVE-2015-8953, CVE-2015-8955, CVE-2015-8956, CVE-2015-8961, CVE-2015-8962, CVE-2015-8963, CVE-2015-8964, CVE-2015-8966, CVE-2015-8967, CVE-2015-8970, CVE-2015-9004, CVE-2015-9016, CVE-2015-9289, CVE-2016-0617, CVE-2016-0723, CVE-2016-0728, CVE-2016-0758, CVE-2016-0821, CVE-2016-0823, CVE-2016-10044, CVE-2016-10088, CVE-2016-10147, CVE-2016-10150, CVE-2016-10153, CVE-2016-10154,

CVE-2016-10200, CVE-2016-10208, CVE-2016-10229, CVE-2016-10318, CVE-2016-10723, CVE-2016-10741, CVE-2016-10764, CVE-2016-10905, CVE-2016-10906, CVE-2016-10907, CVE-2016-1237, CVE-2016-1575, CVE-2016-1576, CVE-2016-1583, CVE-2016-2053, CVE-2016-2069, CVE-2016-2070, CVE-2016-2085, CVE-2016-2117, CVE-2016-2143, CVE-2016-2184, CVE-2016-2185, CVE-2016-2186, CVE-2016-2187, CVE-2016-2188, CVE-2016-2383, CVE-2016-2384, CVE-2016-2543, CVE-2016-2544, CVE-2016-2545, CVE-2016-2546, CVE-2016-2547, CVE-2016-2548, CVE-2016-2549, CVE-2016-2550, CVE-2016-2782, CVE-2016-2847, CVE-2016-3044, CVE-2016-3070, CVE-2016-3134, CVE-2016-3135, CVE-2016-3136, CVE-2016-3137, CVE-2016-3138, CVE-2016-3139, CVE-2016-3140, CVE-2016-3156, CVE-2016-3157, CVE-2016-3672, CVE-2016-3689, CVE-2016-3713, CVE-2016-3841, CVE-2016-3857, CVE-2016-3951, CVE-2016-3955, CVE-2016-3961, CVE-2016-4440, CVE-2016-4470, CVE-2016-4482, CVE-2016-4485, CVE-2016-4486, CVE-2016-4557, CVE-2016-4558, CVE-2016-4565, CVE-2016-4568, CVE-2016-4569, CVE-2016-4578, CVE-2016-4580, CVE-2016-4581, CVE-2016-4794, CVE-2016-4805, CVE-2016-4913, CVE-2016-4951, CVE-2016-4997, CVE-2016-4998, CVE-2016-5195, CVE-2016-5243, CVE-2016-5244, CVE-2016-5400, CVE-2016-5412, CVE-2016-5696, CVE-2016-5728, CVE-2016-5828, CVE-2016-5829, CVE-2016-6130, CVE-2016-6136, CVE-2016-6156, CVE-2016-6162, CVE-2016-6187, CVE-2016-6197, CVE-2016-6198, CVE-2016-6213, CVE-2016-6327, CVE-2016-6480, CVE-2016-6516, CVE-2016-6786, CVE-2016-6787, CVE-2016-6828, CVE-2016-7039, CVE-2016-7042, CVE-2016-7097, CVE-2016-7117, CVE-2016-7425, CVE-2016-7910, CVE-2016-7911, CVE-2016-7912, CVE-2016-7913, CVE-2016-7914, CVE-2016-7915, CVE-2016-7916, CVE-2016-7917, CVE-2016-8399, CVE-2016-8405, CVE-2016-8630, CVE-2016-8632, CVE-2016-8633, CVE-2016-8636, CVE-2016-8645, CVE-2016-8646, CVE-2016-8650, CVE-2016-8655, CVE-2016-8658, CVE-2016-8666, CVE-2016-9083, CVE-2016-9084, CVE-2016-9120, CVE-2016-9178, CVE-2016-9191, CVE-2016-9313, CVE-2016-9555, CVE-2016-9576, CVE-2016-9588, CVE-2016-9604, CVE-2016-9685, CVE-2016-9754, CVE-2016-9755, CVE-2016-9756, CVE-2016-9777, CVE-2016-9793, CVE-2016-9794, CVE-2016-9806, CVE-2016-9919, CVE-2017-0605, CVE-2017-0627, CVE-2017-0750, CVE-2017-0786, CVE-2017-0861, CVE-2017-1000, CVE-2017-1000111, CVE-2017-1000112, CVE-2017-1000251, CVE-2017-1000252, CVE-2017-1000253, CVE-2017-1000255, CVE-2017-1000363, CVE-2017-1000364, CVE-2017-1000365, CVE-2017-1000370, CVE-2017-1000371, CVE-2017-1000379, CVE-2017-1000380, CVE-2017-1000405, CVE-2017-1000407, CVE-2017-1000410, CVE-2017-10661, CVE-2017-10662, CVE-2017-10663, CVE-2017-10810, CVE-2017-10911, CVE-2017-11089, CVE-2017-11176, CVE-2017-11472, CVE-2017-11473, CVE-2017-11600, CVE-2017-12134, CVE-2017-12146, CVE-2017-12153, CVE-2017-12154, CVE-2017-12168, CVE-2017-12188, CVE-2017-12190, CVE-2017-12192, CVE-2017-12193, CVE-2017-12762, CVE-2017-13080, CVE-2017-13166, CVE-2017-13167, CVE-2017-13168, CVE-2017-13215, CVE-2017-13216, CVE-2017-13220, CVE-2017-13305, CVE-2017-13686, CVE-2017-13695, CVE-2017-13715, CVE-2017-14051, CVE-2017-14106, CVE-2017-14140, CVE-2017-14156, CVE-2017-14340, CVE-2017-14489, CVE-2017-14497, CVE-2017-14954, CVE-2017-14991, CVE-2017-15102, CVE-2017-15115, CVE-2017-15116, CVE-2017-15121, CVE-2017-15126, CVE-2017-15127, CVE-2017-15128, CVE-2017-15129, CVE-2017-15265, CVE-2017-15274, CVE-2017-15299, CVE-2017-15306, CVE-2017-15537, CVE-2017-15649, CVE-2017-15868, CVE-2017-15951, CVE-2017-16525, CVE-2017-16526, CVE-2017-16527, CVE-2017-16528, CVE-2017-16529, CVE-2017-16530, CVE-2017-16531, CVE-2017-16532, CVE-2017-16533, CVE-2017-16534, CVE-2017-16535, CVE-2017-16536, CVE-2017-16537, CVE-2017-16538, CVE-2017-16643, CVE-2017-16644, CVE-2017-16645, CVE-2017-16646, CVE-2017-16647, CVE-2017-16648, CVE-2017-16649, CVE-2017-16650, CVE-2017-16911, CVE-2017-16912, CVE-2017-16913, CVE-2017-16914, CVE-2017-16939, CVE-2017-16994, CVE-2017-16995, CVE-2017-16996, CVE-2017-17052, CVE-2017-17053, CVE-2017-17448, CVE-2017-17449, CVE-2017-17450, CVE-2017-17558, CVE-2017-17712, CVE-2017-

17741, CVE-2017-17805, CVE-2017-17806, CVE-2017-17807, CVE-2017-17852, CVE-2017-17853, CVE-2017-17854, CVE-2017-17855, CVE-2017-17856, CVE-2017-17857, CVE-2017-17862, CVE-2017-17863, CVE-2017-17864, CVE-2017-17975, CVE-2017-18017, CVE-2017-18075, CVE-2017-18079, CVE-2017-18174, CVE-2017-18193, CVE-2017-18200, CVE-2017-18202, CVE-2017-18203, CVE-2017-18204, CVE-2017-18208, CVE-2017-18216, CVE-2017-18218, CVE-2017-18221, CVE-2017-18222, CVE-2017-18224, CVE-2017-18232, CVE-2017-18241, CVE-2017-18249, CVE-2017-18255, CVE-2017-18257, CVE-2017-18261, CVE-2017-18270, CVE-2017-18344, CVE-2017-18360, CVE-2017-18379, CVE-2017-18509, CVE-2017-18549, CVE-2017-18550, CVE-2017-18551, CVE-2017-18552, CVE-2017-18595, CVE-2017-2583, CVE-2017-2584, CVE-2017-2596, CVE-2017-2618, CVE-2017-2634, CVE-2017-2636, CVE-2017-2647, CVE-2017-2671, CVE-2017-5123, CVE-2017-5546, CVE-2017-5547, CVE-2017-5548, CVE-2017-5549, CVE-2017-5550, CVE-2017-5551, CVE-2017-5576, CVE-2017-5577, CVE-2017-5669, CVE-2017-5715, CVE-2017-5753, CVE-2017-5754, CVE-2017-5897, CVE-2017-5967, CVE-2017-5970, CVE-2017-5972, CVE-2017-5986, CVE-2017-6001, CVE-2017-6074, CVE-2017-6214, CVE-2017-6345, CVE-2017-6346, CVE-2017-6347, CVE-2017-6348, CVE-2017-6353, CVE-2017-6874, CVE-2017-6951, CVE-2017-7184, CVE-2017-7187, CVE-2017-7261, CVE-2017-7273, CVE-2017-7277, CVE-2017-7294, CVE-2017-7308, CVE-2017-7346, CVE-2017-7374, CVE-2017-7472, CVE-2017-7477, CVE-2017-7482, CVE-2017-7487, CVE-2017-7495, CVE-2017-7518, CVE-2017-7533, CVE-2017-7541, CVE-2017-7542, CVE-2017-7558, CVE-2017-7616, CVE-2017-7618, CVE-2017-7645, CVE-2017-7889, CVE-2017-7895, CVE-2017-7979, CVE-2017-8061, CVE-2017-8062, CVE-2017-8063, CVE-2017-8064, CVE-2017-8065, CVE-2017-8066, CVE-2017-8067, CVE-2017-8068, CVE-2017-8069, CVE-2017-8070, CVE-2017-8071, CVE-2017-8072, CVE-2017-8106, CVE-2017-8240, CVE-2017-8797, CVE-2017-8824, CVE-2017-8831, CVE-2017-8890, CVE-2017-8924, CVE-2017-8925, CVE-2017-9059, CVE-2017-9074, CVE-2017-9075, CVE-2017-9076, CVE-2017-9077, CVE-2017-9150, CVE-2017-9211, CVE-2017-9242, CVE-2017-9605, CVE-2017-9725, CVE-2017-9984, CVE-2017-9985, CVE-2017-9986, CVE-2018-1000004, CVE-2018-1000026, CVE-2018-1000028, CVE-2018-1000199, CVE-2018-1000200, CVE-2018-1000204, CVE-2018-10021, CVE-2018-10074, CVE-2018-10087, CVE-2018-10124, CVE-2018-10322, CVE-2018-10323, CVE-2018-1065, CVE-2018-1066, CVE-2018-10675, CVE-2018-1068, CVE-2018-10840, CVE-2018-10853, CVE-2018-1087, CVE-2018-10876, CVE-2018-10877, CVE-2018-10878, CVE-2018-10879, CVE-2018-10880, CVE-2018-10881, CVE-2018-10882, CVE-2018-10883, CVE-2018-10901, CVE-2018-10902, CVE-2018-1091, CVE-2018-1092, CVE-2018-1093, CVE-2018-10938, CVE-2018-1094, CVE-2018-10940, CVE-2018-1095, CVE-2018-1108, CVE-2018-1118, CVE-2018-1120, CVE-2018-11232, CVE-2018-1128, CVE-2018-1129, CVE-2018-1130, CVE-2018-11412, CVE-2018-11506, CVE-2018-11508, CVE-2018-12126, CVE-2018-12127, CVE-2018-12130, CVE-2018-12207, CVE-2018-12232, CVE-2018-12233, CVE-2018-12633, CVE-2018-12714, CVE-2018-12896, CVE-2018-12904, CVE-2018-13053, CVE-2018-13093, CVE-2018-13094, CVE-2018-13095, CVE-2018-13096, CVE-2018-13097, CVE-2018-13098, CVE-2018-13099, CVE-2018-13100, CVE-2018-13405, CVE-2018-13406, CVE-2018-14609, CVE-2018-14610, CVE-2018-14611, CVE-2018-14612, CVE-2018-14613, CVE-2018-14614, CVE-2018-14615, CVE-2018-14616, CVE-2018-14617, CVE-2018-14619, CVE-2018-14625, CVE-2018-14633, CVE-2018-14634, CVE-2018-14641, CVE-2018-14646, CVE-2018-14656, CVE-2018-14678, CVE-2018-14734, CVE-2018-15471, CVE-2018-15572, CVE-2018-15594, CVE-2018-16276, CVE-2018-16597, CVE-2018-16658, CVE-2018-16862, CVE-2018-16871, CVE-2018-16880, CVE-2018-16882, CVE-2018-16884, CVE-2018-17182, CVE-2018-17972, CVE-2018-18021, CVE-2018-18281, CVE-2018-18386, CVE-2018-18397, CVE-2018-18445, CVE-2018-18559, CVE-2018-18690, CVE-2018-18710, CVE-2018-18955, CVE-2018-19406, CVE-2018-19407, CVE-2018-19824, CVE-2018-19854, CVE-2018-19985, CVE-2018-20169, CVE-2018-20449, CVE-2018-20509, CVE-2018-20510, CVE-2018-20511,

CVE-2018-20669, CVE-2018-20784, CVE-2018-20836, CVE-2018-20854, CVE-2018-20855, CVE-2018-20856, CVE-2018-20961, CVE-2018-20976, CVE-2018-21008, CVE-2018-25015, CVE-2018-25020, CVE-2018-3620, CVE-2018-3639, CVE-2018-3646, CVE-2018-3665, CVE-2018-3693, CVE-2018-5332, CVE-2018-5333, CVE-2018-5344, CVE-2018-5390, CVE-2018-5391, CVE-2018-5703, CVE-2018-5750, CVE-2018-5803, CVE-2018-5814, CVE-2018-5848, CVE-2018-5873, CVE-2018-5953, CVE-2018-5995, CVE-2018-6412, CVE-2018-6554, CVE-2018-6555, CVE-2018-6927, CVE-2018-7191, CVE-2018-7273, CVE-2018-7480, CVE-2018-7492, CVE-2018-7566, CVE-2018-7740, CVE-2018-7754, CVE-2018-7755, CVE-2018-7757, CVE-2018-7995, CVE-2018-8043, CVE-2018-8087, CVE-2018-8781, CVE-2018-8822, CVE-2018-8897, CVE-2018-9363, CVE-2018-9385, CVE-2018-9415, CVE-2018-9422, CVE-2018-9465, CVE-2018-9516, CVE-2018-9517, CVE-2018-9518, CVE-2018-9568, CVE-2019-0136, CVE-2019-0145, CVE-2019-0146, CVE-2019-0147, CVE-2019-0148, CVE-2019-0149, CVE-2019-0154, CVE-2019-0155, CVE-2019-10124, CVE-2019-10125, CVE-2019-10126, CVE-2019-10142, CVE-2019-10207, CVE-2019-10220, CVE-2019-10638, CVE-2019-10639, CVE-2019-11085, CVE-2019-11091, CVE-2019-11135, CVE-2019-11190, CVE-2019-11191, CVE-2019-1125, CVE-2019-11477, CVE-2019-11478, CVE-2019-11479, CVE-2019-11486, CVE-2019-11487, CVE-2019-11599, CVE-2019-11683, CVE-2019-11810, CVE-2019-11811, CVE-2019-11815, CVE-2019-11833, CVE-2019-11884, CVE-2019-12378, CVE-2019-12379, CVE-2019-12380, CVE-2019-12381, CVE-2019-12382, CVE-2019-12454, CVE-2019-12455, CVE-2019-12614, CVE-2019-12615, CVE-2019-12817, CVE-2019-12818, CVE-2019-12819, CVE-2019-12881, CVE-2019-12984, CVE-2019-13233, CVE-2019-13272, CVE-2019-13631, CVE-2019-13648, CVE-2019-14283, CVE-2019-14284, CVE-2019-14615, CVE-2019-14763, CVE-2019-14814, CVE-2019-14815, CVE-2019-14816, CVE-2019-14821, CVE-2019-14835, CVE-2019-14895, CVE-2019-14896, CVE-2019-14897, CVE-2019-14901, CVE-2019-15030, CVE-2019-15031, CVE-2019-15090, CVE-2019-15098, CVE-2019-15099, CVE-2019-15117, CVE-2019-15118, CVE-2019-15211, CVE-2019-15212, CVE-2019-15213, CVE-2019-15214, CVE-2019-15215, CVE-2019-15216, CVE-2019-15217, CVE-2019-15218, CVE-2019-15219, CVE-2019-15220, CVE-2019-15221, CVE-2019-15222, CVE-2019-15223, CVE-2019-15291, CVE-2019-15292, CVE-2019-15504, CVE-2019-15505, CVE-2019-15538, CVE-2019-15666, CVE-2019-15807, CVE-2019-15916, CVE-2019-15917, CVE-2019-15918, CVE-2019-15919, CVE-2019-15920, CVE-2019-15921, CVE-2019-15922, CVE-2019-15923, CVE-2019-15924, CVE-2019-15925, CVE-2019-15926, CVE-2019-15927, CVE-2019-16229, CVE-2019-16230, CVE-2019-16231, CVE-2019-16232, CVE-2019-16233, CVE-2019-16234, CVE-2019-16413, CVE-2019-16714, CVE-2019-16746, CVE-2019-16921, CVE-2019-16994, CVE-2019-16995, CVE-2019-17052, CVE-2019-17053, CVE-2019-17054, CVE-2019-17055, CVE-2019-17056, CVE-2019-17075, CVE-2019-17133, CVE-2019-17351, CVE-2019-17666, CVE-2019-18198, CVE-2019-18282, CVE-2019-18660, CVE-2019-18675, CVE-2019-18683, CVE-2019-18786, CVE-2019-18805, CVE-2019-18806, CVE-2019-18807, CVE-2019-18808, CVE-2019-18809, CVE-2019-18810, CVE-2019-18811, CVE-2019-18812, CVE-2019-18813, CVE-2019-18814, CVE-2019-18885, CVE-2019-19036, CVE-2019-19037, CVE-2019-19039, CVE-2019-19043, CVE-2019-19044, CVE-2019-19045, CVE-2019-19046, CVE-2019-19047, CVE-2019-19048, CVE-2019-19049, CVE-2019-19050, CVE-2019-19051, CVE-2019-19052, CVE-2019-19053, CVE-2019-19054, CVE-2019-19055, CVE-2019-19056, CVE-2019-19057, CVE-2019-19058, CVE-2019-19059, CVE-2019-19060, CVE-2019-19061, CVE-2019-19062, CVE-2019-19063, CVE-2019-19064, CVE-2019-19065, CVE-2019-19066, CVE-2019-19067, CVE-2019-19068, CVE-2019-19069, CVE-2019-19070, CVE-2019-19071, CVE-2019-19072, CVE-2019-19073, CVE-2019-19074, CVE-2019-19075, CVE-2019-19076, CVE-2019-19077, CVE-2019-19078, CVE-2019-19079, CVE-2019-19080, CVE-2019-19081, CVE-2019-19082, CVE-2019-19083, CVE-2019-19227, CVE-2019-19241, CVE-2019-19252, CVE-2019-19318, CVE-2019-19319, CVE-2019-19332, CVE-2019-19338, CVE-2019-19377, CVE-2019-19447,

CVE-2019-19448, CVE-2019-19449, CVE-2019-19462, CVE-2019-19523, CVE-2019-19524, CVE-2019-19525, CVE-2019-19526, CVE-2019-19527, CVE-2019-19528, CVE-2019-19529, CVE-2019-19530, CVE-2019-19531, CVE-2019-19532, CVE-2019-19533, CVE-2019-19534, CVE-2019-19535, CVE-2019-19536, CVE-2019-19537, CVE-2019-19543, CVE-2019-19602, CVE-2019-19767, CVE-2019-19768, CVE-2019-19769, CVE-2019-19770, CVE-2019-19807, CVE-2019-19813, CVE-2019-19815, CVE-2019-19816, CVE-2019-19922, CVE-2019-19927, CVE-2019-19947, CVE-2019-19965, CVE-2019-19966, CVE-2019-1999, CVE-2019-20054, CVE-2019-20095, CVE-2019-20096, CVE-2019-2024, CVE-2019-2025, CVE-2019-20422, CVE-2019-2054, CVE-2019-20636, CVE-2019-20806, CVE-2019-20810, CVE-2019-20811, CVE-2019-20812, CVE-2019-20908, CVE-2019-20934, CVE-2019-2101, CVE-2019-2181, CVE-2019-2182, CVE-2019-2213, CVE-2019-2214, CVE-2019-2215, CVE-2019-25044, CVE-2019-25045, CVE-2019-3016, CVE-2019-3459, CVE-2019-3460, CVE-2019-3701, CVE-2019-3819, CVE-2019-3837, CVE-2019-3846, CVE-2019-3874, CVE-2019-3882, CVE-2019-3887, CVE-2019-3892, CVE-2019-3896, CVE-2019-3900, CVE-2019-3901, CVE-2019-5108, CVE-2019-6133, CVE-2019-6974, CVE-2019-7221, CVE-2019-7222, CVE-2019-7308, CVE-2019-8912, CVE-2019-8956, CVE-2019-8980, CVE-2019-9003, CVE-2019-9162, CVE-2019-9213, CVE-2019-9245, CVE-2019-9444, CVE-2019-9445, CVE-2019-9453, CVE-2019-9454, CVE-2019-9455, CVE-2019-9456, CVE-2019-9457, CVE-2019-9458, CVE-2019-9466, CVE-2019-9500, CVE-2019-9503, CVE-2019-9506, CVE-2019-9857, CVE-2020-0009, CVE-2020-0030, CVE-2020-0041, CVE-2020-0066, CVE-2020-0067, CVE-2020-0110, CVE-2020-0255, CVE-2020-0305, CVE-2020-0404, CVE-2020-0423, CVE-2020-0427, CVE-2020-0429, CVE-2020-0430, CVE-2020-0431, CVE-2020-0432, CVE-2020-0433, CVE-2020-0435, CVE-2020-0444, CVE-2020-0465, CVE-2020-0466, CVE-2020-0543, CVE-2020-10135, CVE-2020-10690, CVE-2020-10711, CVE-2020-10720, CVE-2020-10732, CVE-2020-10742, CVE-2020-10751, CVE-2020-10757, CVE-2020-10766, CVE-2020-10767, CVE-2020-10768, CVE-2020-10769, CVE-2020-10773, CVE-2020-10781, CVE-2020-10942, CVE-2020-11494, CVE-2020-11565, CVE-2020-11608, CVE-2020-11609, CVE-2020-11668, CVE-2020-11669, CVE-2020-11884, CVE-2020-12114, CVE-2020-12351, CVE-2020-12352, CVE-2020-12464, CVE-2020-12465, CVE-2020-12652, CVE-2020-12653, CVE-2020-12654, CVE-2020-12655, CVE-2020-12656, CVE-2020-12657, CVE-2020-12659, CVE-2020-12768, CVE-2020-12769, CVE-2020-12770, CVE-2020-12771, CVE-2020-12826, CVE-2020-12888, CVE-2020-12912, CVE-2020-13143, CVE-2020-13974, CVE-2020-14305, CVE-2020-14314, CVE-2020-14331, CVE-2020-14351, CVE-2020-14353, CVE-2020-14356, CVE-2020-14381, CVE-2020-14385, CVE-2020-14386, CVE-2020-14390, CVE-2020-14416, CVE-2020-15393, CVE-2020-15436, CVE-2020-15437, CVE-2020-15780, CVE-2020-15852, CVE-2020-16119, CVE-2020-16120, CVE-2020-16166, CVE-2020-1749, CVE-2020-24394, CVE-2020-24490, CVE-2020-24586, CVE-2020-24587, CVE-2020-24588, CVE-2020-25211, CVE-2020-25212, CVE-2020-25221, CVE-2020-25284, CVE-2020-25285, CVE-2020-25639, CVE-2020-25641, CVE-2020-25643, CVE-2020-25645, CVE-2020-25656, CVE-2020-25668, CVE-2020-25669, CVE-2020-25670, CVE-2020-25671, CVE-2020-25672, CVE-2020-25673, CVE-2020-25704, CVE-2020-25705, CVE-2020-26088, CVE-2020-26139, CVE-2020-26141, CVE-2020-26145, CVE-2020-26147, CVE-2020-26541, CVE-2020-26555, CVE-2020-26558, CVE-2020-27066, CVE-2020-27067, CVE-2020-27068, CVE-2020-27152, CVE-2020-27170, CVE-2020-27171, CVE-2020-27194, CVE-2020-2732, CVE-2020-27418, CVE-2020-27673, CVE-2020-27675, CVE-2020-27777, CVE-2020-27784, CVE-2020-27786, CVE-2020-27815, CVE-2020-27820, CVE-2020-27825, CVE-2020-27830, CVE-2020-27835, CVE-2020-28097, CVE-2020-28374, CVE-2020-28588, CVE-2020-28915, CVE-2020-28941, CVE-2020-28974, CVE-2020-29368, CVE-2020-29369, CVE-2020-29370, CVE-2020-29371, CVE-2020-29372, CVE-2020-29373, CVE-2020-29374, CVE-2020-29534, CVE-2020-29568, CVE-2020-29569, CVE-2020-29660, CVE-2020-29661, CVE-2020-35499, CVE-2020-35508, CVE-2020-35513, CVE-2020-35519, CVE-2020-36158,

CVE-2020-36310, CVE-2020-36311, CVE-2020-36312, CVE-2020-36313, CVE-2020-36322, CVE-2020-36385, CVE-2020-36386, CVE-2020-36387, CVE-2020-36516, CVE-2020-36557, CVE-2020-36558, CVE-2020-36691, CVE-2020-36694, CVE-2020-36766, CVE-2020-3702, CVE-2020-4788, CVE-2020-7053, CVE-2020-8428, CVE-2020-8647, CVE-2020-8648, CVE-2020-8649, CVE-2020-8694, CVE-2020-8834, CVE-2020-8835, CVE-2020-8992, CVE-2020-9383, CVE-2020-9391, CVE-2021-0129, CVE-2021-0342, CVE-2021-0447, CVE-2021-0448, CVE-2021-0512, CVE-2021-0605, CVE-2021-0707, CVE-2021-0920, CVE-2021-0929, CVE-2021-0935, CVE-2021-0937, CVE-2021-0938, CVE-2021-0941, CVE-2021-1048, CVE-2021-20177, CVE-2021-20194, CVE-2021-20226, CVE-2021-20239, CVE-2021-20261, CVE-2021-20265, CVE-2021-20268, CVE-2021-20292, CVE-2021-20317, CVE-2021-20320, CVE-2021-20321, CVE-2021-20322, CVE-2021-21781, CVE-2021-22543, CVE-2021-22555, CVE-2021-22600, CVE-2021-23133, CVE-2021-23134, CVE-2021-26401, CVE-2021-26708, CVE-2021-26930, CVE-2021-26931, CVE-2021-26932, CVE-2021-27363, CVE-2021-27364, CVE-2021-27365, CVE-2021-28038, CVE-2021-28039, CVE-2021-28375, CVE-2021-28660, CVE-2021-28688, CVE-2021-28691, CVE-2021-28711, CVE-2021-28712, CVE-2021-28713, CVE-2021-28714, CVE-2021-28715, CVE-2021-28950, CVE-2021-28951, CVE-2021-28952, CVE-2021-28964, CVE-2021-28971, CVE-2021-28972, CVE-2021-29154, CVE-2021-29155, CVE-2021-29264, CVE-2021-29265, CVE-2021-29266, CVE-2021-29646, CVE-2021-29647, CVE-2021-29648, CVE-2021-29649, CVE-2021-29650, CVE-2021-29657, CVE-2021-30002, CVE-2021-30178, CVE-2021-31440, CVE-2021-3178, CVE-2021-31829, CVE-2021-31916, CVE-2021-32399, CVE-2021-32606, CVE-2021-33033, CVE-2021-33034, CVE-2021-33098, CVE-2021-33135, CVE-2021-33200, CVE-2021-3347, CVE-2021-3348, CVE-2021-33624, CVE-2021-33655, CVE-2021-33656, CVE-2021-33909, CVE-2021-3411, CVE-2021-3428, CVE-2021-3444, CVE-2021-34556, CVE-2021-34693, CVE-2021-3483, CVE-2021-34866, CVE-2021-3489, CVE-2021-3490, CVE-2021-3491, CVE-2021-34981, CVE-2021-3501, CVE-2021-35039, CVE-2021-3506, CVE-2021-3543, CVE-2021-35477, CVE-2021-3564, CVE-2021-3573, CVE-2021-3587, CVE-2021-3600, CVE-2021-3609, CVE-2021-3612, CVE-2021-3635, CVE-2021-3640, CVE-2021-3653, CVE-2021-3655, CVE-2021-3656, CVE-2021-3659, CVE-2021-3679, CVE-2021-3715, CVE-2021-37159, CVE-2021-3732, CVE-2021-3736, CVE-2021-3739, CVE-2021-3743, CVE-2021-3744, CVE-2021-3752, CVE-2021-3753, CVE-2021-37576, CVE-2021-3759, CVE-2021-3760, CVE-2021-3764, CVE-2021-3772, CVE-2021-38160, CVE-2021-38166, CVE-2021-38198, CVE-2021-38199, CVE-2021-38200, CVE-2021-38201, CVE-2021-38202, CVE-2021-38203, CVE-2021-38204, CVE-2021-38205, CVE-2021-38206, CVE-2021-38207, CVE-2021-38208, CVE-2021-38209, CVE-2021-38300, CVE-2021-3894, CVE-2021-3896, CVE-2021-3923, CVE-2021-39633, CVE-2021-39634, CVE-2021-39636, CVE-2021-39648, CVE-2021-39656, CVE-2021-39657, CVE-2021-39685, CVE-2021-39686, CVE-2021-39698, CVE-2021-39711, CVE-2021-39713, CVE-2021-39714, CVE-2021-4001, CVE-2021-4002, CVE-2021-4028, CVE-2021-4032, CVE-2021-4037, CVE-2021-40490, CVE-2021-4083, CVE-2021-4090, CVE-2021-4093, CVE-2021-4095, CVE-2021-41073, CVE-2021-4135, CVE-2021-4148, CVE-2021-4149, CVE-2021-4154, CVE-2021-4155, CVE-2021-4157, CVE-2021-4159, CVE-2021-41864, CVE-2021-4197, CVE-2021-42008, CVE-2021-4202, CVE-2021-4203, CVE-2021-4218, CVE-2021-42252, CVE-2021-42327, CVE-2021-42739, CVE-2021-43056, CVE-2021-43057, CVE-2021-43267, CVE-2021-43389, CVE-2021-43975, CVE-2021-43976, CVE-2021-44733, CVE-2021-45095, CVE-2021-45100, CVE-2021-45402, CVE-2021-45469, CVE-2021-45480, CVE-2021-45485, CVE-2021-45486, CVE-2021-45868, CVE-2021-46283, CVE-2022-0001, CVE-2022-0002, CVE-2022-0168, CVE-2022-0171, CVE-2022-0185, CVE-2022-0264, CVE-2022-0286, CVE-2022-0322, CVE-2022-0330, CVE-2022-0433, CVE-2022-0435, CVE-2022-0487, CVE-2022-0492, CVE-2022-0494, CVE-2022-0516, CVE-2022-0617, CVE-2022-0644, CVE-2022-0646, CVE-2022-0742, CVE-2022-0812, CVE-2022-0847, CVE-2022-0850, CVE-2022-0854, CVE-2022-0995, CVE-2022-1011, CVE-



2022-1012, CVE-2022-1015, CVE-2022-1016, CVE-2022-1043, CVE-2022-1048, CVE-2022-1055, CVE-2022-1158, CVE-2022-1184, CVE-2022-1195, CVE-2022-1198, CVE-2022-1199, CVE-2022-1204, CVE-2022-1205, CVE-2022-1353, CVE-2022-1419, CVE-2022-1462, CVE-2022-1516, CVE-2022-1651, CVE-2022-1652, CVE-2022-1671, CVE-2022-1678, CVE-2022-1679, CVE-2022-1729, CVE-2022-1734, CVE-2022-1786, CVE-2022-1789, CVE-2022-1836, CVE-2022-1852, CVE-2022-1882, CVE-2022-1943, CVE-2022-1966, CVE-2022-1972, CVE-2022-1973, CVE-2022-1974, CVE-2022-1975, CVE-2022-1976, CVE-2022-1998, CVE-2022-20008, CVE-2022-20132, CVE-2022-20141, CVE-2022-20153, CVE-2022-20154, CVE-2022-20158, CVE-2022-20166, CVE-2022-20368, CVE-2022-20369, CVE-2022-20421, CVE-2022-20422, CVE-2022-20423, CVE-2022-20565, CVE-2022-20566, CVE-2022-20567, CVE-2022-20572, CVE-2022-2078, CVE-2022-21123, CVE-2022-21125, CVE-2022-21166, CVE-2022-21385, CVE-2022-21499, CVE-2022-21505, CVE-2022-2153, CVE-2022-2196, CVE-2022-22942, CVE-2022-23036, CVE-2022-23037, CVE-2022-23038, CVE-2022-23039, CVE-2022-23040, CVE-2022-23041, CVE-2022-23042, CVE-2022-2308, CVE-2022-2318, CVE-2022-2380, CVE-2022-23816, CVE-2022-23960, CVE-2022-24122, CVE-2022-24448, CVE-2022-24958, CVE-2022-24959, CVE-2022-2503, CVE-2022-25258, CVE-2022-25375, CVE-2022-25636, CVE-2022-2585, CVE-2022-2586, CVE-2022-2588, CVE-2022-2590, CVE-2022-2602, CVE-2022-26365, CVE-2022-26373, CVE-2022-2639, CVE-2022-26490, CVE-2022-2663, CVE-2022-26966, CVE-2022-27223, CVE-2022-27666, CVE-2022-2785, CVE-2022-27950, CVE-2022-28356, CVE-2022-28388, CVE-2022-28389, CVE-2022-28390, CVE-2022-2873, CVE-2022-28796, CVE-2022-28893, CVE-2022-2905, CVE-2022-29156, CVE-2022-2938, CVE-2022-29581, CVE-2022-29582, CVE-2022-2959, CVE-2022-2964, CVE-2022-2977, CVE-2022-2978, CVE-2022-29900, CVE-2022-29901, CVE-2022-29968, CVE-2022-3028, CVE-2022-30594, CVE-2022-3061, CVE-2022-3077, CVE-2022-3078, CVE-2022-3103, CVE-2022-3104, CVE-2022-3105, CVE-2022-3106, CVE-2022-3107, CVE-2022-3110, CVE-2022-3111, CVE-2022-3112, CVE-2022-3113, CVE-2022-3114, CVE-2022-3115, CVE-2022-3169, CVE-2022-3170, CVE-2022-3202, CVE-2022-32250, CVE-2022-32296, CVE-2022-3239, CVE-2022-32981, CVE-2022-3303, CVE-2022-33740, CVE-2022-33741, CVE-2022-33742, CVE-2022-33743, CVE-2022-33744, CVE-2022-33981, CVE-2022-3424, CVE-2022-3435, CVE-2022-34494, CVE-2022-34495, CVE-2022-34918, CVE-2022-3521, CVE-2022-3524, CVE-2022-3526, CVE-2022-3531, CVE-2022-3532, CVE-2022-3534, CVE-2022-3535, CVE-2022-3541, CVE-2022-3542, CVE-2022-3543, CVE-2022-3545, CVE-2022-3564, CVE-2022-3565, CVE-2022-3577, CVE-2022-3586, CVE-2022-3594, CVE-2022-36123, CVE-2022-3619, CVE-2022-3621, CVE-2022-3623, CVE-2022-3625, CVE-2022-3628, CVE-2022-36280, CVE-2022-3629, CVE-2022-3630, CVE-2022-3633, CVE-2022-3635, CVE-2022-3640, CVE-2022-3643, CVE-2022-3646, CVE-2022-3649, CVE-2022-36879, CVE-2022-36946, CVE-2022-3707, CVE-2022-3910, CVE-2022-39189, CVE-2022-39190, CVE-2022-3977, CVE-2022-39842, CVE-2022-40307, CVE-2022-40476, CVE-2022-40768, CVE-2022-4095, CVE-2022-40982, CVE-2022-41218, CVE-2022-41222, CVE-2022-4127, CVE-2022-4128, CVE-2022-4129, CVE-2022-4139, CVE-2022-41674, CVE-2022-41849, CVE-2022-41850, CVE-2022-41858, CVE-2022-42328, CVE-2022-42329, CVE-2022-42432, CVE-2022-4269, CVE-2022-42703, CVE-2022-42719, CVE-2022-42720, CVE-2022-42721, CVE-2022-42722, CVE-2022-42895, CVE-2022-42896, CVE-2022-43750, CVE-2022-4378, CVE-2022-4379, CVE-2022-4382, CVE-2022-43945, CVE-2022-45869, CVE-2022-45886, CVE-2022-45887, CVE-2022-45888, CVE-2022-45919, CVE-2022-45934, CVE-2022-4662, CVE-2022-4744, CVE-2022-47518, CVE-2022-47519, CVE-2022-47520, CVE-2022-47521, CVE-2022-47929, CVE-2022-47938, CVE-2022-47939, CVE-2022-47940, CVE-2022-47941, CVE-2022-47942, CVE-2022-47943, CVE-2022-4842, CVE-2022-48423, CVE-2022-48424, CVE-2022-48425, CVE-2022-48502, CVE-2023-0030, CVE-2023-0045, CVE-2023-0047, CVE-2023-0122, CVE-2023-0160, CVE-2023-0179, CVE-2023-0210, CVE-2023-0240, CVE-2023-0266, CVE-2023-0394, CVE-2023-0458, CVE-2023-0459, CVE-2023-

0461, CVE-2023-0468, CVE-2023-0469, CVE-2023-0590, CVE-2023-0615, CVE-2023-1032, CVE-2023-1073, CVE-2023-1074, CVE-2023-1076, CVE-2023-1077, CVE-2023-1078, CVE-2023-1079, CVE-2023-1095, CVE-2023-1118, CVE-2023-1192, CVE-2023-1194, CVE-2023-1195, CVE-2023-1206, CVE-2023-1249, CVE-2023-1252, CVE-2023-1281, CVE-2023-1380, CVE-2023-1382, CVE-2023-1390, CVE-2023-1513, CVE-2023-1582, CVE-2023-1583, CVE-2023-1611, CVE-2023-1637, CVE-2023-1652, CVE-2023-1670, CVE-2023-1829, CVE-2023-1838, CVE-2023-1855, CVE-2023-1859, CVE-2023-1989, CVE-2023-1990, CVE-2023-1998, CVE-2023-2002, CVE-2023-2006, CVE-2023-2008, CVE-2023-2019, CVE-2023-20569, CVE-2023-20588, CVE-2023-20593, CVE-2023-20938, CVE-2023-21102, CVE-2023-21106, CVE-2023-2124, CVE-2023-21255, CVE-2023-21264, CVE-2023-2156, CVE-2023-2162, CVE-2023-2163, CVE-2023-2166, CVE-2023-2177, CVE-2023-2194, CVE-2023-2235, CVE-2023-2236, CVE-2023-2248, CVE-2023-2269, CVE-2023-22996, CVE-2023-22997, CVE-2023-22998, CVE-2023-22999, CVE-2023-23001, CVE-2023-23002, CVE-2023-23003, CVE-2023-23004, CVE-2023-23005, CVE-2023-23006, CVE-2023-23454, CVE-2023-23455, CVE-2023-23559, CVE-2023-2483, CVE-2023-25012, CVE-2023-2513, CVE-2023-25775, CVE-2023-2598, CVE-2023-26544, CVE-2023-26545, CVE-2023-26605, CVE-2023-26606, CVE-2023-26607, CVE-2023-28327, CVE-2023-28328, CVE-2023-28410, CVE-2023-28464, CVE-2023-28466, CVE-2023-2860, CVE-2023-28772, CVE-2023-28866, CVE-2023-2898, CVE-2023-2985, CVE-2023-3006, CVE-2023-30456, CVE-2023-30772, CVE-2023-3090, CVE-2023-3106, CVE-2023-3111, CVE-2023-3117, CVE-2023-31248, CVE-2023-3141, CVE-2023-31436, CVE-2023-3159, CVE-2023-3161, CVE-2023-3212, CVE-2023-3220, CVE-2023-32233, CVE-2023-32247, CVE-2023-32248, CVE-2023-32250, CVE-2023-32252, CVE-2023-32254, CVE-2023-32257, CVE-2023-32258, CVE-2023-32269, CVE-2023-3268, CVE-2023-3269, CVE-2023-3312, CVE-2023-3317, CVE-2023-33203, CVE-2023-33250, CVE-2023-33288, CVE-2023-3338, CVE-2023-3355, CVE-2023-3357, CVE-2023-3358, CVE-2023-3359, CVE-2023-3390, CVE-2023-33951, CVE-2023-33952, CVE-2023-34255, CVE-2023-34256, CVE-2023-34319, CVE-2023-3439, CVE-2023-35001, CVE-2023-3567, CVE-2023-35788, CVE-2023-35823, CVE-2023-35824, CVE-2023-35826, CVE-2023-35828, CVE-2023-35829, CVE-2023-3609, CVE-2023-3610, CVE-2023-3611, CVE-2023-37453, CVE-2023-3772, CVE-2023-3773, CVE-2023-3776, CVE-2023-3777, CVE-2023-3812, CVE-2023-38409, CVE-2023-38426, CVE-2023-38427, CVE-2023-38428, CVE-2023-38429, CVE-2023-38430, CVE-2023-38431, CVE-2023-38432, CVE-2023-3863, CVE-2023-3865, CVE-2023-3866, CVE-2023-3867, CVE-2023-39189, CVE-2023-39192, CVE-2023-39193, CVE-2023-39194, CVE-2023-4004, CVE-2023-4015, CVE-2023-40283, CVE-2023-4128, CVE-2023-4132, CVE-2023-4147, CVE-2023-4155, CVE-2023-4194, CVE-2023-4206, CVE-2023-4207, CVE-2023-4208, CVE-2023-4273, CVE-2023-42752, CVE-2023-42753, CVE-2023-42755, CVE-2023-42756, CVE-2023-4385, CVE-2023-4387, CVE-2023-4389, CVE-2023-4394, CVE-2023-44466, CVE-2023-4459, CVE-2023-4569, CVE-2023-45862, CVE-2023-45871, CVE-2023-4611, CVE-2023-4623, CVE-2023-4732, CVE-2023-4921 and CVE-2023-5345

- **linux-yocto/5.15:** Ignore CVE-2022-45886, CVE-2022-45887, CVE-2022-45919, CVE-2022-48502, CVE-2023-0160, CVE-2023-1206, CVE-2023-20593, CVE-2023-21264, CVE-2023-2898, CVE-2023-31248, CVE-2023-33250, CVE-2023-34319, CVE-2023-35001, CVE-2023-3611, CVE-2023-37453, CVE-2023-3773, CVE-2023-3776, CVE-2023-3777, CVE-2023-38432, CVE-2023-3863, CVE-2023-3865, CVE-2023-3866, CVE-2023-4004, CVE-2023-4015, CVE-2023-4132, CVE-2023-4147, CVE-2023-4194, CVE-2023-4385, CVE-2023-4387, CVE-2023-4389, CVE-2023-4394, CVE-2023-4459 and CVE-2023-4611
- **openssl:** Fix CVE-2023-4807 and CVE-2023-5363
- **python3-git:** Fix CVE-2023-40590 and CVE-2023-41040



- python3-urllib3: Fix [CVE-2023-43804](#)
- qemu: Ignore [CVE-2023-2680](#)
- ruby: Fix [CVE-2023-36617](#)
- shadow: Fix [CVE-2023-4641](#)
- tiff: Fix [CVE-2023-3576](#) and [CVE-2023-40745](#)
- vim: Fix [CVE-2023-5441](#) and [CVE-2023-5535](#)
- webkitgtk: Fix [CVE-2023-32439](#)
- xdg-utils: Fix [CVE-2022-4055](#)
- xserver-xorg: ignore [CVE-2022-3553](#) (XQuartz-specific)
- zlib: Fix [CVE-2023-45853](#)

### Fixes in Yocto-4.0.14

- SECURITY.md: Add file
- apt: add missing <stdint> for uint16\_t
- bind: update to 9.18.19
- bitbake: SECURITY.md: add file
- bitbake: bitbake-getvar: Add a quiet command line argument
- bitbake: bitbake-worker/runqueue: Avoid unnecessary bytes object copies
- brief-yoctoprojectqs: use new CDN mirror for sstate
- bsp-guide: bsp.rst: replace reference to wiki
- bsp-guide: bsp: skip Intel machines no longer supported in Poky
- build-appliance-image: Update to kirkstone head revision
- ccache: fix build with gcc-13
- cml1: Fix KCONFIG\_CONFIG\_COMMAND not conveyed fully in do\_menuconfig
- contributor-guide/style-guide: Add a note about task idempotence
- contributor-guide/style-guide: Refer to recipes, not packages
- contributor-guide: deprecate "Accepted" patch status
- contributor-guide: discourage marking patches as Inappropriate
- contributor-guide: recipe-style-guide: add more patch tagging examples
- contributor-guide: recipe-style-guide: add section about CVE patches
- contributor-guide: style-guide: discourage using Pending patch status
- dev-manual: add security team processes
- dev-manual: fix testimage usage instructions

- dev-manual: layers: Add notes about layer.conf
- dev-manual: new-recipe.rst: add missing parenthesis to "Patching Code" section
- dev-manual: new-recipe.rst: replace reference to wiki
- dev-manual: start.rst: remove obsolete reference
- dev-manual: wic: update "wic list images" output
- dev/ref-manual: Document *INIT\_MANAGER*
- fontcache.bbclass: avoid native recipes depending on target fontconfig
- glibc: Update to latest on stable 2.35 branch (c84018a05aec..)
- json-c: define *CVE\_VERSION*
- kernel.bbclass: Add force flag to rm calls
- libxpm: upgrade to 3.5.17
- linux-firmware: create separate packages
- linux-firmware: upgrade to 20230804
- linux-yocto/5.10: update to v5.10.197
- linux-yocto: update CVE exclusions
- manuals: correct "yocto-linux" by "linux-yocto"
- manuals: update linux-yocto append examples
- migration-guides: add release notes for 4.0.13
- openssl: Upgrade to 3.0.12
- overview: Add note about non-reproducibility side effects
- package\_rpm: Allow compression mode override
- poky.conf: bump version for 4.0.14
- profile-manual: aesthetic cleanups
- python3-git: upgrade to 3.1.37
- python3-jinja2: fix for the ptest result format
- python3-urllib3: upgrade to 1.26.17
- ref-manual: Fix *PACKAGECONFIG* term and add an example
- ref-manual: Warn about *COMPATIBLE\_MACHINE* skipping native recipes
- ref-manual: releases.svg: Scarthgap is now version 5.0
- ref-manual: variables: add *RECIPE\_SYSROOT* and *RECIPE\_SYSROOT\_NATIVE*
- ref-manual: variables: add *TOOLCHAIN\_OPTIONS* variable
- ref-manual: variables: add example for *SYSROOT\_DIRS* variable

- ref-manual: variables: provide no-match example for *COMPATIBLE\_MACHINE*
- sdk-manual: appendix-obtain: improve and update descriptions
- test-manual: reproducible-builds: stop mentioning LTO bug
- uboot-extlinux-config.bbclass: fix missed override syntax migration
- vim: Upgrade to 9.0.2048

### Known Issues in Yocto-4.0.14

- N/A

### Contributors to Yocto-4.0.14

- Alexander Kanavin
- Archana Polampalli
- Armin Kuster
- Arne Schwerdt
- BELHADJ SALEM Talel
- Bruce Ashfield
- Chaitanya Vadrevu
- Colin McAllister
- Deepthi Hemraj
- Etienne Cordonnier
- Fahad Arslan
- Hitendra Prajapati
- Jaeyoon Jung
- Joshua Watt
- Khem Raj
- Lee Chee Yang
- Marta Rybczynska
- Martin Jansa
- Meenali Gupta
- Michael Opdenacker
- Narpat Mali
- Niko Mauno
- Paul Eggleton
- Paulo Neves

- Peter Marko
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Roland Hieber
- Ross Burton
- Ryan Eatmon
- Shubham Kulkarni
- Siddharth Doshi
- Soumya Sambu
- Steve Sakoman
- Tim Orling
- Trevor Gamblin
- Vijay Anusuri
- Wang Mingyu
- Yash Shinde
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.14

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.14](#)
- Git Revision: [d8d6d921fad14b82167d9f031d4fca06b5e01883](#)
- Release Artefact: [poky-d8d6d921fad14b82167d9f031d4fca06b5e01883](#)
- sha: [46a6301e3921ee67cfe6be7ea544d6257f0c0f02ef15c5091287e024ff02d5f5](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.14/poky-d8d6d921fad14b82167d9f031d4fca06b5e01883.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.14/poky-d8d6d921fad14b82167d9f031d4fca06b5e01883.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.14](#)
- Git Revision: [0eb8e67aa6833df0cde29833568a70e65c21d7e5](#)

- Release Artefact: oecore-0eb8e67aa6833df0cde29833568a70e65c21d7e5
- sha: d510a7067b87ba935b8a7c9f9608d0e06b057009ea753ed190ddfacc7195ecc5
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.14/oecore-0eb8e67aa6833df0cde29833568a70e65c21d7e5.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.14/oecore-0eb8e67aa6833df0cde29833568a70e65c21d7e5.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.14
- Git Revision: f6b38ce3c90e1600d41c2ebb41e152936a0357d7
- Release Artefact: meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7
- sha: 7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.14/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.14/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.14
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.14/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.14/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.14
- Git Revision: 6c1ffa9091d0c53a100e8c8c15122d28642034bd
- Release Artefact: bitbake-6c1ffa9091d0c53a100e8c8c15122d28642034bd
- sha: 1ceffc3b3359063341530c989a3606c897d862b61111538e683f101b02a360a2
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.14/bitbake-6c1ffa9091d0c53a100e8c8c15122d28642034bd.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.14/bitbake-6c1ffa9091d0c53a100e8c8c15122d28642034bd.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.14`
- Git Revision: `260b446a1a75d99399a3421cd8d6ba276f508f37`

### 17.11.17 Release notes for Yocto-4.0.15 (Kirkstone)

#### Security Fixes in Yocto-4.0.15

- avahi: Fix CVE-2023-1981, CVE-2023-38469, CVE-2023-38470, CVE-2023-38471, CVE-2023-38472 and CVE-2023-38473
- binutils: Fix CVE-2022-47007, CVE-2022-47010 and CVE-2022-48064
- bluez5: Fix CVE-2023-45866
- ghostscript: Ignore GhostPCL CVE-2023-38560
- gnutls: Fix CVE-2023-5981
- go: Ignore CVE-2023-45283 and CVE-2023-45284
- grub: Fix CVE-2023-4692 and CVE-2023-4693
- gstreamer1.0-plugins-bad: Fix CVE-2023-44429
- libsndfile: Fix CVE-2022-33065
- libwebp: Fix CVE-2023-4863
- openssl: Fix CVE-2023-5678
- python3-cryptography: Fix CVE-2023-49083
- qemu: Fix CVE-2023-1544
- sudo: CVE-2023-42456 and CVE-2023-42465
- tiff: Fix CVE-2023-41175
- vim: Fix CVE-2023-46246, CVE-2023-48231, CVE-2023-48232, CVE-2023-48233, CVE-2023-48234, CVE-2023-48235, CVE-2023-48236, CVE-2023-48237 and CVE-2023-48706
- xserver-xorg: Fix CVE-2023-5367 and CVE-2023-5380
- xwayland: Fix CVE-2023-5367

#### Fixes in Yocto-4.0.15

- bash: changes to SIGINT handler while waiting for a child
- bitbake: Fix disk space monitoring on cephfs
- bitbake: bitbake-getvar: Make --quiet work with --recipe
- bitbake: runqueue.py: fix PSI check logic

- bitbake: runqueue: Add pressure change logging
- bitbake: runqueue: convert deferral messages from bb.note to bb.debug
- bitbake: runqueue: fix PSI check calculation
- bitbake: runqueue: show more pressure data
- bitbake: runqueue: show number of currently running bitbake threads when pressure changes
- bitbake: tinfoil: Do not fail when logging is disabled and full config is used
- build-appliance-image: Update to kirkstone head revision
- cve-check: don't warn if a patch is remote
- cve-check: slightly more verbose warning when adding the same package twice
- cve-check: sort the package list in the JSON report
- cve-exclusion\_5.10.inc: update for 5.10.202
- go: Fix issue in DNS resolver
- goarch: Move Go architecture mapping to a library
- gstreamer1.0-plugins-base: enable glx/opengl support
- linux-yocto/5.10: update to v5.10.202
- manuals: update class references
- migration-guide: add release notes for 4.0.14
- native: Clear TUNE\_FEATURES/ABIEXTENSION
- openssh: drop sudo from ptest dependencies
- overview-manual: concepts: Add Bitbake Tasks Map
- poky.conf: bump version for 4.0.15
- python3-jinja2: Fixed ptest result output as per the standard
- ref-manual: classes: explain cml1 class name
- ref-manual: update *SDK\_NAME* variable documentation
- ref-manual: variables: add *RECIPE\_MAINTAINER*
- ref-manual: variables: document OEQA\_REPRODUCIBLE\_\* variables
- ref-manual: variables: mention new CDN for *SSTATE\_MIRRORS*
- rust-common: Set llvm-target correctly for cross SDK targets
- rust-cross-canadian: Fix ordering of target json config generation
- rust-cross/rust-common: Merge arm target handling code to fix cross-canadian
- rust-cross: Simplify the rust\_gen\_target calls
- rust-llvm: Allow overriding LLVM target archs

- sdk-manual: extensible.rst: remove instructions for using SDK functionality directly in a yocto build
- sudo: upgrade to 1.9.15p2
- systemtap\_git: fix used uninitialized error
- vim: Improve locale handling
- vim: Upgrade to 9.0.2130
- vim: use upstream generated .po files

### **Known Issues in Yocto-4.0.15**

- N/A

### **Contributors to Yocto-4.0.15**

- Alexander Kanavin
- Archana Polampalli
- BELHADJ SALEM Talel
- Bruce Ashfield
- Chaitanya Vadrevu
- Chen Qi
- Deepthi Hemraj
- Denys Dmytriienko
- Hitendra Prajapati
- Lee Chee Yang
- Li Wang
- Martin Jansa
- Meenali Gupta
- Michael Odenacker
- Mikko Rapeli
- Narpat Mali
- Niko Mauno
- Ninad Palsule
- Niranjana Pradhan
- Paul Eggleton
- Peter Kjellerstedt
- Peter Marko
- Richard Purdie



- Ross Burton
- Samantha Jalabert
- Sanjana
- Soumya Sambu
- Steve Sakoman
- Tim Orling
- Vijay Anusuri
- Vivek Kumbhar
- Wenlin Kang
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.15

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.15](#)
- Git Revision: [755632c2fcab43aa05cdcfa529727064b045073c](#)
- Release Artefact: [poky-755632c2fcab43aa05cdcfa529727064b045073c](#)
- sha: [b40b43bd270d21a420c399981f9cfe0eb999f15e051fc2c89d124f249cdc0bd5](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.15/poky-755632c2fcab43aa05cdcfa529727064b045073c.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.15/poky-755632c2fcab43aa05cdcfa529727064b045073c.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.15](#)
- Git Revision: [eea685e1caafd8e8121006d3f8b5d0b8a4f2a933](#)
- Release Artefact: [oecore-eea685e1caafd8e8121006d3f8b5d0b8a4f2a933](#)
- sha: [ddc3d4a2c8a097f2aa7132ae716affacc44b119c616a1eeffb7db56caa7fc79e](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.15/oecore-eea685e1caafd8e8121006d3f8b5d0b8a4f2a933.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.15/oecore-eea685e1caafd8e8121006d3f8b5d0b8a4f2a933.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>

- Branch: `kirkstone`
- Tag: `yocto-4.0.15`
- Git Revision: `f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- Release Artefact: `meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- sha: `7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.15/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.15/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.15`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.15/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.15/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.15`
- Git Revision: `42a1c9fe698a03feb34c5bba223c6e6e0350925b`
- Release Artefact: `bitbake-42a1c9fe698a03feb34c5bba223c6e6e0350925b`
- sha: `64c684ccd661fa13e25c859dfc68d66bec79281da0f4f81b0d6a9995acb659b5`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.15/bitbake-42a1c9fe698a03feb34c5bba223c6e6e0350925b.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.15/bitbake-42a1c9fe698a03feb34c5bba223c6e6e0350925b.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.15`
- Git Revision: `08fda7a5601393617b1ecfe89229459e14a90b1d`

## 17.11.18 Release notes for Yocto-4.0.16 (Kirkstone)

### Security Fixes in Yocto-4.0.16

- cpio: Fix [CVE-2023-7207](#)
- curl: Revert "curl: Backport fix [CVE-2023-32001](#)"
- curl: Fix [CVE-2023-46218](#)
- dropbear: Fix [CVE-2023-48795](#)
- ffmpeg: Fix [CVE-2022-3964](#) and [CVE-2022-3965](#)
- ghostscript: Fix [CVE-2023-46751](#)
- gnutls: Fix [CVE-2024-0553](#) and [CVE-2024-0567](#)
- go: Fix [CVE-2023-39326](#)
- openssh: Fix [CVE-2023-48795](#), [CVE-2023-51384](#) and [CVE-2023-51385](#)
- openssl: Fix [CVE-2023-6129](#) and [CVE-2023-6237](#)
- pam: Fix [CVE-2024-22365](#)
- perl: Fix [CVE-2023-47038](#)
- qemu: Fix [CVE-2023-5088](#)
- sqlite3: Fix [CVE-2023-7104](#)
- systemd: Fix [CVE-2023-7008](#)
- tiff: Fix [CVE-2023-6228](#)
- xserver-xorg: Fix [CVE-2023-6377](#), [CVE-2023-6478](#), [CVE-2023-6816](#), [CVE-2024-0229](#), [CVE-2024-0408](#), [CVE-2024-0409](#), [CVE-2024-21885](#) and [CVE-2024-21886](#)
- zlib: Ignore [CVE-2023-6992](#)

### Fixes in Yocto-4.0.16

- bitbake: asynrcpc: Add context manager API
- bitbake: data: Add missing dependency handling of remove operator
- bitbake: lib/bb: Add workaround for libgcc issues with python 3.8 and 3.9
- bitbake: toastergui: verify that an existing layer path is given
- build-appliance-image: Update to kirkstone head revision
- contributor-guide: add License-Update tag
- contributor-guide: fix command option
- contributor-guide: use "apt" instead of "aptitude"
- cpio: upgrade to 2.14
- cve-update-nvd2-native: faster requests with API keys

- cve-update-nvd2-native: increase the delay between subsequent request failures
- cve-update-nvd2-native: make number of fetch attempts configurable
- cve-update-nvd2-native: remove unused variable `CVE_SOCKET_TIMEOUT`
- dev-manual: Discourage the use of `SRC_URI[md5sum]`
- dev-manual: layers: update link to YP Compatible form
- dev-manual: runtime-testing: fix test module name
- dev-manual: start.rst: update use of Download page
- docs:what-i-wish-id-known.rst: fix URL
- docs: document VSCode extension
- docs:brief-yoctoprojectqs:index.rst: align variable order with default `local.conf`
- docs:migration-guides: add release notes for 4.0.15
- docs:migration-guides: release 3.5 is actually 4.0
- elfutils: Disable stringop-overflow warning for build host
- externalsrc: Ensure *SRCREV* is processed before accessing *SRC\_URI*
- linux-firmware: upgrade to 20231030
- manuals: Add *CONVERSION\_CMD* definition
- manuals: Add *UBOOT\_BINARY*, extend *UBOOT\_CONFIG*
- perl: upgrade to 5.34.3
- poky.conf: bump version for 4.0.16
- pybootchartgui: fix 2 SyntaxWarnings
- python3-ptest: skip test\_storlines
- ref-manual: Fix reference to MIRRORS/PREMIRRORS defaults
- ref-manual: classes: remove insserv bbclass
- ref-manual: releases.svg: update nanbield release status
- ref-manual: resources: sync with master branch
- ref-manual: update tested and supported distros
- test-manual: add links to python unittest
- test-manual: add or improve hyperlinks
- test-manual: explicit or fix file paths
- test-manual: resource updates
- test-manual: text and formatting fixes
- test-manual: use working example

- testimage: Exclude wtmp from target-dumper commands
- testimage: drop target\_dumper, host\_dumper, and monitor\_dumper
- tzdata: Upgrade to 2023d

#### Known Issues in Yocto-4.0.16

- N/A

#### Contributors to Yocto-4.0.16

- Aatir Manzur
- Archana Polampalli
- Dhairya Nagodra
- Dmitry Baryshkov
- Enguerrand de Ribaucourt
- Hitendra Prajapati
- Insu Park
- Joshua Watt
- Justin Bronder
- Jörg Sommer
- Khem Raj
- Lee Chee Yang
- mark.yang
- Marta Rybczynska
- Martin Jansa
- Maxin B. John
- Michael Opdenacker
- Paul Barker
- Peter Kjellerstedt
- Peter Marko
- Poonam Jadhav
- Richard Purdie
- Shubham Kulkarni
- Simone Weiß
- Soumya Sambu
- Sourav Pramanik

- Steve Sakoman
- Trevor Gamblin
- Vijay Anusuri
- Vivek Kumbhar
- Yoann Congal
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.16

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.16`
- Git Revision: `54af8c5e80ebf63707ef4e51cc9d374f716da603`
- Release Artefact: `poky-54af8c5e80ebf63707ef4e51cc9d374f716da603`
- sha: `a53ec3a661cf56ca40c0fbf1500288c2c20abe94896d66a572bc5ccf5d92e9d6`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.16/poky-54af8c5e80ebf63707ef4e51cc9d374f716da603.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.16/poky-54af8c5e80ebf63707ef4e51cc9d374f716da603.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.16`
- Git Revision: `a744a897f0ea7d34c31c024c13031221f9a85f24`
- Release Artefact: `oecore-a744a897f0ea7d34c31c024c13031221f9a85f24`
- sha: `8c2bc9487597b0caa9f5a1d72b18cfd1ddc7e6d91f0f051313563d6af95aeec`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.16/oecore-a744a897f0ea7d34c31c024c13031221f9a85f24.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.16/oecore-a744a897f0ea7d34c31c024c13031221f9a85f24.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.16`
- Git Revision: `f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- Release Artefact: `meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7`

- sha: 7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.16/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.16/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.16
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.16/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.16/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.16
- Git Revision: ee090484cc25d760b8c20f18add17b5eff485b40
- Release Artefact: bitbake-ee090484cc25d760b8c20f18add17b5eff485b40
- sha: 479e3a57ae9fbc2aa95292a7554caef113bbfb28c226ed19547b8dde1c95314
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.16/bitbake-ee090484cc25d760b8c20f18add17b5eff485b40.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.16/bitbake-ee090484cc25d760b8c20f18add17b5eff485b40.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.16
- Git Revision: aba67b58711019a6ba439b2b77337f813ed799ac

## 17.11.19 Release notes for Yocto-4.0.17 (Kirkstone)

### Security Fixes in Yocto-4.0.17

- bind: Fix CVE-2023-4408, CVE-2023-5517, CVE-2023-5679, CVE-2023-50868 and CVE-2023-50387
- binutils: Fix CVE-2023-39129 and CVE-2023-39130

- curl: Fix CVE-2023-46219
- curl: Ignore CVE-2023-42915
- gcc: Ignore CVE-2023-4039
- gdb: Fix CVE-2023-39129 and CVE-2023-39130
- glibc: Ignore CVE-2023-0687
- go: Fix CVE-2023-29406, CVE-2023-45285, CVE-2023-45287, CVE-2023-45289, CVE-2023-45290, CVE-2024-24784 and CVE-2024-24785
- less: Fix CVE-2022-48624
- libgit2: Fix CVE-2024-24575 and CVE-2024-24577
- libuv: fix CVE-2024-24806
- libxml2: Fix for CVE-2024-25062
- linux-yocto/5.15: Fix CVE-2022-36402, CVE-2022-40982, CVE-2022-47940, CVE-2023-1193, CVE-2023-1194, CVE-2023-3772, CVE-2023-3867, CVE-2023-4128, CVE-2023-4206, CVE-2023-4207, CVE-2023-4208, CVE-2023-4244, CVE-2023-4273, CVE-2023-4563, CVE-2023-4569, CVE-2023-4623, CVE-2023-4881, CVE-2023-4921, CVE-2023-5158, CVE-2023-5717, CVE-2023-6040, CVE-2023-6121, CVE-2023-6176, CVE-2023-6546, CVE-2023-6606, CVE-2023-6622, CVE-2023-6817, CVE-2023-6915, CVE-2023-6931, CVE-2023-6932, CVE-2023-20569, CVE-2023-20588, CVE-2023-25775, CVE-2023-31085, CVE-2023-32247, CVE-2023-32250, CVE-2023-32252, CVE-2023-32254, CVE-2023-32257, CVE-2023-32258, CVE-2023-34324, CVE-2023-35827, CVE-2023-38427, CVE-2023-38430, CVE-2023-38431, CVE-2023-39189, CVE-2023-39192, CVE-2023-39193, CVE-2023-39194, CVE-2023-39198, CVE-2023-40283, CVE-2023-42752, CVE-2023-42753, CVE-2023-42754, CVE-2023-42755, CVE-2023-45871, CVE-2023-46343, CVE-2023-46813, CVE-2023-46838, CVE-2023-46862, CVE-2023-51042, CVE-2023-51779, CVE-2023-52340, CVE-2023-52429, CVE-2023-52435, CVE-2023-52436, CVE-2023-52438, CVE-2023-52439, CVE-2023-52441, CVE-2023-52442, CVE-2023-52443, CVE-2023-52444, CVE-2023-52445, CVE-2023-52448, CVE-2023-52449, CVE-2023-52451, CVE-2023-52454, CVE-2023-52456, CVE-2023-52457, CVE-2023-52458, CVE-2023-52463, CVE-2023-52464, CVE-2024-0340, CVE-2024-0584, CVE-2024-0607, CVE-2024-0641, CVE-2024-0646, CVE-2024-1085, CVE-2024-1086, CVE-2024-1151, CVE-2024-22705, CVE-2024-23849, CVE-2024-23850, CVE-2024-23851, CVE-2024-24860, CVE-2024-26586, CVE-2024-26589, CVE-2024-26591, CVE-2024-26592, CVE-2024-26593, CVE-2024-26594, CVE-2024-26597 and CVE-2024-26598
- linux-yocto/5.15: Ignore CVE-2020-27418, CVE-2020-36766, CVE-2021-33630, CVE-2021-33631, CVE-2022-48619, CVE-2023-2430, CVE-2023-4610, CVE-2023-4732, CVE-2023-5090, CVE-2023-5178, CVE-2023-5197, CVE-2023-5345, CVE-2023-5633, CVE-2023-5972, CVE-2023-6111, CVE-2023-6200, CVE-2023-6531, CVE-2023-6679, CVE-2023-7192, CVE-2023-40791, CVE-2023-42756, CVE-2023-44466, CVE-2023-45862, CVE-2023-45863, CVE-2023-45898, CVE-2023-51043, CVE-2023-51780, CVE-2023-51781, CVE-2023-51782, CVE-2023-52433, CVE-2023-52440, CVE-2023-52446, CVE-2023-52450, CVE-2023-52453, CVE-2023-52455, CVE-2023-52459, CVE-2023-52460, CVE-2023-52461, CVE-2023-52462, CVE-2024-0193, CVE-2024-0443, CVE-2024-0562, CVE-2024-0582, CVE-2024-0639, CVE-2024-0775, CVE-2024-26581, CVE-2024-26582, CVE-2024-26590, CVE-2024-26596 and CVE-2024-26599



- linux-yocto/5.10: Fix CVE-2023-6040, CVE-2023-6121, CVE-2023-6606, CVE-2023-6817, CVE-2023-6915, CVE-2023-6931, CVE-2023-6932, CVE-2023-39198, CVE-2023-46838, CVE-2023-51779, CVE-2023-51780, CVE-2023-51781, CVE-2023-51782, CVE-2023-52340, CVE-2024-0584 and CVE-2024-0646
- linux-yocto/5.10: Ignore CVE-2021-33630, CVE-2021-33631, CVE-2022-1508, CVE-2022-36402, CVE-2022-48619, CVE-2023-2430, CVE-2023-4610, CVE-2023-5972, CVE-2023-6039, CVE-2023-6200, CVE-2023-6531, CVE-2023-6546, CVE-2023-6622, CVE-2023-6679, CVE-2023-7192, CVE-2023-46343, CVE-2023-51042, CVE-2023-51043, CVE-2024-0193, CVE-2024-0443, CVE-2024-0562, CVE-2024-0582, CVE-2024-0639, CVE-2024-0641, CVE-2024-0775, CVE-2024-1085 and CVE-2024-22705
- openssl: Fix CVE-2024-0727
- python3-pycryptodome: Fix CVE-2023-52323
- qemu: Fix CVE-2023-6693, CVE-2023-42467 and CVE-2024-24474
- vim: Fix CVE-2024-22667
- xwayland: Fix CVE-2023-6377 and CVE-2023-6478

### Fixes in Yocto-4.0.17

- bind: Upgrade to 9.18.24
- bitbake: bitbake/codeparser.py: address ast module deprecations in py 3.12
- bitbake: bitbake/lib/bs4/tests/test\_tree.py: python 3.12 regex
- bitbake: codeparser: replace deprecated ast.Str and 's'
- bitbake: fetch2: Ensure that git LFS objects are available
- bitbake: tests/fetch: Add real git lfs tests and decorator
- bitbake: tests/fetch: git-lfs restore \_find\_git\_lfs
- bitbake: toaster/toastergui: Bug-fix verify given layer path only if import/add local layer
- build-appliance-image: Update to kirkstone head revision
- cmake: Unset CMAKE\_CXX\_IMPLICIT\_INCLUDE\_DIRECTORIES
- contributor-guide: fix lore URL
- curl: don't enable debug builds
- cve\_check: cleanup logging
- dbus: Add missing *CVE\_PRODUCT*
- dev-manual: sbom: Rephrase spdx creation
- dev-manual: runtime-testing: gen-tapdevs need iptables installed
- dev-manual: packages: clarify shared *PR* service constraint
- dev-manual: packages: need enough free space
- dev-manual: start: remove idle line

- feature-microblaze-versions.inc: python 3.12 regex
- ghostscript: correct *LICENSE* with AGPLv3
- image-live.bbclass: LIVE\_ROOTFS\_TYPE support compression
- kernel.bbclass: Set pkg-config variables for building modules
- kernel.bbclass: introduce KERNEL\_LOCALVERSION
- kernel: fix localversion in v6.3+
- kernel: make LOCALVERSION consistent between recipes
- ldconfig-native: Fix to point correctly on the DT\_NEEDED entries in an ELF file
- librsvg: Fix do\_package\_qa error for librsvg
- linux-firmware: upgrade to 20231211
- linux-yocto/5.10: update to v5.10.210
- linux-yocto/5.15: update to v5.15.150
- manuals: add minimum RAM requirements
- manuals: suppress excess use of "following" word
- manuals: update disk space requirements
- manuals: update references to buildtools
- manuals: updates for building on Windows (WSL 2)
- meta/lib/oeqa: python 3.12 regex
- meta/recipes: python 3.12 regex
- migration-guide: add release notes for 4.0.16
- oeqa/selftest/oelib/buildhistory: git default branch
- oeqa/selftest/recipeptool: downgrade meson version to not use pyproject.toml
- oeqa/selftest/recipeptool: expect meson.bb
- oeqa/selftest/recipeptool: fix for python 3.12
- oeqa/selftest/runtime\_test: only run the virgl tests on qemux86-64
- oeqa: replace deprecated assertEquals
- openssl: Upgrade to 3.0.13
- poky.conf: bump version for 4.0.17
- populate\_sdk\_ext: use ConfigParser instead of SafeConfigParser
- python3-jinja2: upgrade to 3.1.3
- recipeptool/create\_buildsys\_python: use importlib instead of imp
- ref-manual: system-requirements: recommend buildtools for not supported distros

- ref-manual: system-requirements: add info on buildtools-make-tarball
- ref-manual: release-process: grammar fix
- ref-manual: system-requirements: fix AlmaLinux variable name
- ref-manual: system-requirements: modify anchor
- ref-manual: system-requirements: remove outdated note
- ref-manual: system-requirements: simplify supported distro requirements
- ref-manual: system-requirements: update packages to build docs
- scripts/runqemu: add qmp socket support
- scripts/runqemu: direct mesa to use its own drivers, rather than ones provided by host distro
- scripts/runqemu: fix regex escape sequences
- scripts: python 3.12 regex
- selftest: skip virgl gtk/sdl test on ubuntu 18.04
- systemd: Only add myhostname to nsswitch.conf if in *PACKAGECONFIG*
- tzdata : Upgrade to 2024a
- u-boot: Move UBOOT\_INITIAL\_ENV back to u-boot.inc
- useradd-example: do not use unsupported clear text password
- vim: upgrade to v9.0.2190
- yocto-bsp: update to v5.15.150

#### Known Issues in Yocto-4.0.17

- N/A

#### Contributors to Yocto-4.0.17

- Adrian Freihofer
- Alassane Yattara
- Alexander Kanavin
- Alexander Sverdlin
- Archana Polampalli
- Baruch Siach
- Bruce Ashfield
- Chen Qi
- Chris Laplante
- Deepthi Hemraj
- Dhairya Nagodra

- Fabien Mahot
- Fabio Estevam
- Hitendra Prajapati
- Hugo SIMELIERE
- Jermain Horsman
- Kai Kang
- Lee Chee Yang
- Ludovic Jozeau
- Michael Opdenacker
- Ming Liu
- Munehisa Kamata
- Narpat Mali
- Nikhil R
- Paul Eggleton
- Paulo Neves
- Peter Marko
- Philip Lorenz
- Poonam Jadhav
- Priyal Doshi
- Ross Burton
- Simone Weiß
- Soumya Sambu
- Steve Sakoman
- Tim Orling
- Trevor Gamblin
- Vijay Anusuri
- Vivek Kumbhar
- Wang Mingyu
- Zahir Hussain

## Repositories / Downloads for Yocto-4.0.17

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.17`
- Git Revision: `6d1a878bbf24c66f7186b270f823cdf82e35383`
- Release Artefact: `poky-6d1a878bbf24c66f7186b270f823cdf82e35383`
- sha: `3bc3010340b674f7b0dd0a7997f0167b2240b794fbd4aa28c0c4217bddd15e30`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.17/poky-6d1a878bbf24c66f7186b270f823cdf82e35383.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.17/poky-6d1a878bbf24c66f7186b270f823cdf82e35383.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.17`
- Git Revision: `2501534c9581c6c3439f525d630be11554a57d24`
- Release Artefact: `oecore-2501534c9581c6c3439f525d630be11554a57d24`
- sha: `52cc6cce9e920bdce078584b89136e81cc01e0c55616fab5fca6c3e04264c88e`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.17/oecore-2501534c9581c6c3439f525d630be11554a57d24.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.17/oecore-2501534c9581c6c3439f525d630be11554a57d24.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.17`
- Git Revision: `f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- Release Artefact: `meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- sha: `7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.17/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.17/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`

- Tag: `yocto-4.0.17`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.17/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.17/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

### meta-clang

- Repository Location: <https://git.yoctoproject.org/meta-clang>
- Branch: `kirkstone`
- Tag: `yocto-4.0.17`
- Git Revision: `eebe4ff2e539f3ffb01c5060cc4ca8b226ea8b52`
- Release Artefact: `meta-clang-eebe4ff2e539f3ffb01c5060cc4ca8b226ea8b52`
- sha: `3299e96e069a22c0971e903fbc191f2427effc83d910ac51bf0237caad01d17`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.17/meta-clang-eebe4ff2e539f3ffb01c5060cc4ca8b226ea8b52.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.17/meta-clang-eebe4ff2e539f3ffb01c5060cc4ca8b226ea8b52.tar.bz2>

### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.17`
- Git Revision: `40fd5f4eef7460ca67f32cfce8e229e67e1ff607`
- Release Artefact: `bitbake-40fd5f4eef7460ca67f32cfce8e229e67e1ff607`
- sha: `5d20a0e4c5d0fce44bd84778168714a261a30a4b83f67c88df3b8a7e7115e444`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.17/bitbake-40fd5f4eef7460ca67f32cfce8e229e67e1ff607.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.17/bitbake-40fd5f4eef7460ca67f32cfce8e229e67e1ff607.tar.bz2>

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.17`
- Git Revision: `08ce7db2aa3a38deb8f5aa59bafc78542986babb`

## 17.11.20 Release notes for Yocto-4.0.18 (Kirkstone)

### Security Fixes in Yocto-4.0.18

- curl: Fix [CVE-2024-2398](#)
- expat: fix [CVE-2023-52426](#) and [CVE-2024-28757](#)
- libssh2: fix [CVE-2023-48795](#)
- ncurses: Fix [CVE-2023-50495](#)
- nghttp2: Fix [CVE-2024-28182](#) and [CVE-2023-44487](#)
- openssh: Ignore [CVE-2023-51767](#)
- openssl: Fix [CVE-2024-2511](#)
- perl: Ignore [CVE-2023-47100](#)
- python3-cryptography: Fix [CVE-2024-26130](#)
- python3-urllib3: Fix [CVE-2023-45803](#)
- qemu: Fix [CVE-2023-6683](#)
- ruby: fix [CVE-2024-27281](#)
- rust: Ignore [CVE-2024-24576](#)
- tiff: Fix [CVE-2023-52356](#) and [CVE-2023-6277](#)
- xserver-xorg: Fix [CVE-2024-31080](#) and [CVE-2024-31081](#)
- xwayland: Fix [CVE-2023-6816](#), [CVE-2024-0408](#) and [CVE-2024-0409](#)

### Fixes in Yocto-4.0.18

- build-appliance-image: Update to kirkstone head revision
- common-licenses: backport LGPL-3.0-with-zeromq-exception license
- contributor-guide: add notes for tests
- contributor-guide: be more specific about meta-\* trees
- cups: fix typo in [CVE-2023-32360](#) backport patch
- cve-update-nvd2-native: Add an age threshold for incremental update
- cve-update-nvd2-native: Fix CVE configuration update
- cve-update-nvd2-native: Fix typo in comment
- cve-update-nvd2-native: Remove duplicated CVE\_CHECK\_DB\_FILE definition
- cve-update-nvd2-native: Remove rejected CVE from database
- cve-update-nvd2-native: nvd\_request\_next: Improve comment
- dev-manual: improve descriptions of 'bitbake -S printdiff'
- dev-manual: packages: fix capitalization

- docs: conf.py: properly escape backslashes for latex\_elements
- gcc: Backport sanitizer fix for 32-bit ALSR
- glibc: Fix subscript typos for get\_nscd\_addresses
- kernel-dev: join mkdir commands with -p
- linux-firmware: Upgrade to 20240220
- manuals: add initial sphinx-lint support
- manuals: add initial stylechecks with Vale
- manuals: document VIRTUAL-RUNTIME variables
- manuals: fix duplicate "stylecheck" target
- manuals: fix incorrect double backticks
- manuals: fix trailing spaces
- manuals: refer to new yocto-patches mailing list wherever appropriate
- manuals: remove tab characters
- manuals: replace hyphens with em dashes
- manuals: use "manual page(s)"
- migration-guides: add release notes for 4.0.17
- poky.conf: bump version for 4.0.18
- profile-manual: usage.rst: fix reference to bug report
- profile-manual: usage.rst: formatting fixes
- profile-manual: usage.rst: further style improvements
- python3-urllib3: Upgrade to v1.26.18
- ref-manual: add documentation of the variable *SPDX\_NAMESPACE\_PREFIX*
- ref-manual: tasks: do\_cleanall: recommend using '-f' instead
- ref-manual: tasks: do\_cleansstate: recommend using '-f' instead for a shared sstate
- ref-manual: variables: adding multiple groups in *GROUPADD\_PARAM*
- ref-manual: variables: correct sdk installation default path
- stress-ng: avoid calling sync during do\_compile
- systemd: Fix vlan qos mapping
- tcl: Add a way to skip ptests
- tcl: skip async and event tests in run-ptest
- tcl: skip timing-dependent tests in run-ptest
- valgrind: skip intermittently failing ptest



- wireless-regdb: Upgrade to 2024.01.23
- yocto-uninative: Update to 4.4 for glibc 2.39

### Known Issues in Yocto-4.0.18

- N/A

### Contributors to Yocto-4.0.18

- Alex Kiernan
- Alex Stewart
- Alexander Kanavin
- BELOUARGA Mohamed
- Claus Stovgaard
- Colin McAllister
- Geoff Parker
- Haitao Liu
- Harish Sadineni
- Johan Bezem
- Jonathan GUILLOT
- Jörg Sommer
- Khem Raj
- Lee Chee Yang
- Luca Ceresoli
- Martin Jansa
- Meenali Gupta
- Michael Halstead
- Michael Opdenacker
- Peter Marko
- Quentin Schulz
- Ross Burton
- Sana Kazi
- Simone Weiß
- Soumya Sambu
- Steve Sakoman
- Tan Wen Yan

- Vijay Anusuri
- Wang Mingyu
- Yoann Congal
- Yogita Urade
- Zahir Hussain

## Repositories / Downloads for Yocto-4.0.18

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.18](#)
- Git Revision: [31751bba1c789f15f574773a659b8017d7bcf440](#)
- Release Artefact: [poky-31751bba1c789f15f574773a659b8017d7bcf440](#)
- sha: [72d5aa65c3c37766ebc24b212740272c1d52342468548f9c070241d3522ad2ca](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.18/poky-31751bba1c789f15f574773a659b8017d7bcf440.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.18/poky-31751bba1c789f15f574773a659b8017d7bcf440.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.18](#)
- Git Revision: [b7182571242dc4e23e5250a449d90348e62a6abc](#)
- Release Artefact: [oecore-b7182571242dc4e23e5250a449d90348e62a6abc](#)
- sha: [6f257e50c10ebae673dcf61a833b3270db6d22781f02f6794a370aac839f1020](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.18/oecore-b7182571242dc4e23e5250a449d90348e62a6abc.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.18/oecore-b7182571242dc4e23e5250a449d90348e62a6abc.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.18](#)
- Git Revision: [f6b38ce3c90e1600d41c2ebb41e152936a0357d7](#)
- Release Artefact: [meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7](#)
- sha: [7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25](#)

- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.18/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.18/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

## meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.18
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.18/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.18/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

## bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.18
- Git Revision: 40fd5f4eef7460ca67f32cfce8e229e67e1ff607
- Release Artefact: bitbake-40fd5f4eef7460ca67f32cfce8e229e67e1ff607
- sha: 5d20a0e4c5d0fce44bd84778168714a261a30a4b83f67c88df3b8a7e7115e444
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.18/bitbake-40fd5f4eef7460ca67f32cfce8e229e67e1ff607.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.18/bitbake-40fd5f4eef7460ca67f32cfce8e229e67e1ff607.tar.bz2>

## yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.18
- Git Revision: fd1423141e7458ba557db465c171b0b4e9063987

## 17.11.21 Release notes for Yocto-4.0.19 (Kirkstone)

### Security Fixes in Yocto-4.0.19

- bluez5: Fix CVE-2023-27349, CVE-2023-50229 and CVE-2023-50230
- ghostscript: Fix CVE-2023-52722, CVE-2024-29510, CVE-2024-33869, CVE-2024-33870 and CVE-2024-33871
- git: Fix CVE-2024-32002, CVE-2024-32004, CVE-2024-32020, CVE-2024-32021 and CVE-2024-32465

- glibc: Fix CVE-2024-2961, CVE-2024-33599, CVE-2024-33600, CVE-2024-33601 and CVE-2024-33602
- gnutls: Fix CVE-2024-28834 and CVE-2024-28835
- go: Fix CVE-2023-45288
- gstreamer1.0-plugins-bad: Fix CVE-2023-44446, CVE-2023-50186 and CVE-2024-0444
- less: Fix CVE-2024-32487
- libarchive: Fix CVE-2024-26256
- libarchive: Fix multiple null deference and heap overflow in pax writer (no CVE assigned)
- linux-yocto/5.15: Fix CVE-2023-6270, CVE-2023-7042, CVE-2023-52447, CVE-2023-52620, CVE-2024-22099, CVE-2024-26622, CVE-2024-26651, CVE-2024-26659, CVE-2024-26688, CVE-2024-26782, CVE-2024-26787, CVE-2024-26788, CVE-2024-26790, CVE-2024-26791, CVE-2024-26793, CVE-2024-26795, CVE-2024-26798, CVE-2024-26801, CVE-2024-26802, CVE-2024-26803, CVE-2024-26804, CVE-2024-26805 and CVE-2024-26809
- linux-yocto/5.15: Ignore CVE-2019-25160, CVE-2019-25162, CVE-2020-36775, CVE-2020-36776, CVE-2020-36777, CVE-2020-36778, CVE-2020-36779, CVE-2020-36780, CVE-2020-36781, CVE-2020-36782, CVE-2020-36783, CVE-2020-36784, CVE-2020-36785, CVE-2020-36786, CVE-2020-36787, CVE-2021-46904, CVE-2021-46905, CVE-2021-46906, CVE-2021-46908, CVE-2021-46909, CVE-2021-46910, CVE-2021-46911, CVE-2021-46912, CVE-2021-46913, CVE-2021-46914, CVE-2021-46915, CVE-2021-46916, CVE-2021-46917, CVE-2021-46918, CVE-2021-46919, CVE-2021-46920, CVE-2021-46921, CVE-2021-46922, CVE-2021-46923, CVE-2021-46924, CVE-2021-46925, CVE-2021-46926, CVE-2021-46927, CVE-2021-46928, CVE-2021-46929, CVE-2021-46930, CVE-2021-46931, CVE-2021-46932, CVE-2021-46933, CVE-2021-46934, CVE-2021-46935, CVE-2021-46936, CVE-2021-46937, CVE-2021-46938, CVE-2021-46939, CVE-2021-46940, CVE-2021-46941, CVE-2021-46942, CVE-2021-46943, CVE-2021-46944, CVE-2021-46945, CVE-2021-46947, CVE-2021-46948, CVE-2021-46949, CVE-2021-46950, CVE-2021-46951, CVE-2021-46952, CVE-2021-46953, CVE-2021-46954, CVE-2021-46955, CVE-2021-46956, CVE-2021-46957, CVE-2021-46958, CVE-2021-46959, CVE-2021-46960, CVE-2021-46961, CVE-2021-46962, CVE-2021-46963, CVE-2021-46964, CVE-2021-46965, CVE-2021-46966, CVE-2021-46967, CVE-2021-46968, CVE-2021-46969, CVE-2021-46970, CVE-2021-46971, CVE-2021-46972, CVE-2021-46973, CVE-2021-46974, CVE-2021-46976, CVE-2021-46977, CVE-2021-46978, CVE-2021-46979, CVE-2021-46980, CVE-2021-46981, CVE-2021-46982, CVE-2021-46983, CVE-2021-46984, CVE-2021-46985, CVE-2021-46986, CVE-2021-46987, CVE-2021-46988, CVE-2021-46989, CVE-2021-46990, CVE-2021-46991, CVE-2021-46992, CVE-2021-46993, CVE-2021-46994, CVE-2021-46995, CVE-2021-46996, CVE-2021-46997, CVE-2021-46998, CVE-2021-46999, CVE-2021-47000, CVE-2021-47001, CVE-2021-47002, CVE-2021-47003, CVE-2021-47004, CVE-2021-47005, CVE-2021-47006, CVE-2021-47007, CVE-2021-47008, CVE-2021-47009, CVE-2021-47010, CVE-2021-47011, CVE-2021-47012, CVE-2021-47013, CVE-2021-47014, CVE-2021-47015, CVE-2021-47016, CVE-2021-47017, CVE-2021-47018, CVE-2021-47019, CVE-2021-47020, CVE-2021-47021, CVE-2021-47022, CVE-2021-47023, CVE-2021-47024, CVE-2021-47025, CVE-2021-47026, CVE-2021-47027, CVE-2021-47028, CVE-2021-47029, CVE-2021-47030, CVE-2021-47031, CVE-2021-47032, CVE-2021-47033, CVE-2021-47034, CVE-2021-47035, CVE-2021-47036, CVE-2021-47037, CVE-2021-47038, CVE-2021-47039, CVE-2021-47040, CVE-2021-47041, CVE-2021-47042, CVE-2021-47043, CVE-2021-47044, CVE-2021-47045, CVE-2021-47046, CVE-2021-47047, CVE-2021-47048, CVE-2021-47049, CVE-2021-47050, CVE-2021-47051, CVE-2021-47052, CVE-2021-47053, CVE-2021-47054, CVE-2021-

47055, CVE-2021-47056, CVE-2021-47057, CVE-2021-47058, CVE-2021-47059, CVE-2021-47060, CVE-2021-47061, CVE-2021-47062, CVE-2021-47063, CVE-2021-47064, CVE-2021-47065, CVE-2021-47066, CVE-2021-47067, CVE-2021-47068, CVE-2021-47069, CVE-2021-47070, CVE-2021-47071, CVE-2021-47072, CVE-2021-47073, CVE-2021-47074, CVE-2021-47075, CVE-2021-47076, CVE-2021-47077, CVE-2021-47078, CVE-2021-47079, CVE-2021-47080, CVE-2021-47081, CVE-2021-47082, CVE-2021-47083, CVE-2021-47086, CVE-2021-47087, CVE-2021-47088, CVE-2021-47089, CVE-2021-47090, CVE-2021-47091, CVE-2021-47092, CVE-2021-47093, CVE-2021-47094, CVE-2021-47095, CVE-2021-47096, CVE-2021-47097, CVE-2021-47098, CVE-2021-47099, CVE-2021-47100, CVE-2021-47101, CVE-2021-47102, CVE-2021-47103, CVE-2021-47104, CVE-2021-47105, CVE-2021-47106, CVE-2021-47107, CVE-2021-47108, CVE-2021-47109, CVE-2021-47110, CVE-2021-47111, CVE-2021-47112, CVE-2021-47113, CVE-2021-47114, CVE-2021-47116, CVE-2021-47117, CVE-2021-47118, CVE-2021-47119, CVE-2021-47120, CVE-2021-47121, CVE-2021-47122, CVE-2021-47123, CVE-2021-47124, CVE-2021-47125, CVE-2021-47126, CVE-2021-47127, CVE-2021-47128, CVE-2021-47129, CVE-2021-47130, CVE-2021-47131, CVE-2021-47132, CVE-2021-47133, CVE-2021-47134, CVE-2021-47135, CVE-2021-47136, CVE-2021-47137, CVE-2021-47138, CVE-2021-47139, CVE-2021-47140, CVE-2021-47141, CVE-2021-47142, CVE-2021-47143, CVE-2021-47144, CVE-2021-47145, CVE-2021-47146, CVE-2021-47147, CVE-2021-47148, CVE-2021-47149, CVE-2021-47150, CVE-2021-47151, CVE-2021-47152, CVE-2021-47153, CVE-2021-47158, CVE-2021-47159, CVE-2021-47160, CVE-2021-47161, CVE-2021-47162, CVE-2021-47163, CVE-2021-47164, CVE-2021-47165, CVE-2021-47166, CVE-2021-47167, CVE-2021-47168, CVE-2021-47169, CVE-2021-47170, CVE-2021-47171, CVE-2021-47172, CVE-2021-47173, CVE-2021-47174, CVE-2021-47175, CVE-2021-47176, CVE-2021-47177, CVE-2021-47178, CVE-2021-47179 and CVE-2021-47180

- **linux-yocto/5.15 (cont.): Ignore** CVE-2022-48626, CVE-2022-48627, CVE-2022-48629, CVE-2022-48630, CVE-2023-6356, CVE-2023-6536, CVE-2023-52434, CVE-2023-52465, CVE-2023-52467, CVE-2023-52468, CVE-2023-52469, CVE-2023-52470, CVE-2023-52471, CVE-2023-52472, CVE-2023-52473, CVE-2023-52474, CVE-2023-52475, CVE-2023-52476, CVE-2023-52477, CVE-2023-52478, CVE-2023-52479, CVE-2023-52480, CVE-2023-52482, CVE-2023-52483, CVE-2023-52484, CVE-2023-52486, CVE-2023-52487, CVE-2023-52489, CVE-2023-52490, CVE-2023-52491, CVE-2023-52492, CVE-2023-52493, CVE-2023-52494, CVE-2023-52495, CVE-2023-52497, CVE-2023-52498, CVE-2023-52499, CVE-2023-52500, CVE-2023-52501, CVE-2023-52502, CVE-2023-52503, CVE-2023-52504, CVE-2023-52505, CVE-2023-52507, CVE-2023-52509, CVE-2023-52510, CVE-2023-52511, CVE-2023-52512, CVE-2023-52513, CVE-2023-52515, CVE-2023-52516, CVE-2023-52517, CVE-2023-52518, CVE-2023-52519, CVE-2023-52520, CVE-2023-52522, CVE-2023-52523, CVE-2023-52524, CVE-2023-52525, CVE-2023-52526, CVE-2023-52527, CVE-2023-52528, CVE-2023-52529, CVE-2023-52531, CVE-2023-52559, CVE-2023-52560, CVE-2023-52562, CVE-2023-52563, CVE-2023-52564, CVE-2023-52566, CVE-2023-52567, CVE-2023-52570, CVE-2023-52573, CVE-2023-52574, CVE-2023-52575, CVE-2023-52577, CVE-2023-52578, CVE-2023-52580, CVE-2023-52581, CVE-2023-52583, CVE-2023-52587, CVE-2023-52588, CVE-2023-52594, CVE-2023-52595, CVE-2023-52597, CVE-2023-52598, CVE-2023-52599, CVE-2023-52600, CVE-2023-52601, CVE-2023-52602, CVE-2023-52603, CVE-2023-52604, CVE-2023-52606, CVE-2023-52607, CVE-2023-52608, CVE-2023-52609, CVE-2023-52610, CVE-2023-52611, CVE-2023-52612, CVE-2023-52613, CVE-2023-52614, CVE-2023-52615, CVE-2023-52616, CVE-2023-52617, CVE-2023-52618, CVE-2023-52619, CVE-2023-52622, CVE-2023-52623, CVE-2023-52626, CVE-2023-52627, CVE-2023-52628, CVE-2023-52630, CVE-2023-52631, CVE-2023-52633, CVE-2023-52635, CVE-2023-52636, CVE-2023-52637, CVE-2023-52638, CVE-2023-52640,

CVE-2023-52641, CVE-2024-0565, CVE-2024-0841, CVE-2024-23196, CVE-2024-26587, CVE-2024-26588, CVE-2024-26600, CVE-2024-26601, CVE-2024-26602, CVE-2024-26603, CVE-2024-26604, CVE-2024-26605, CVE-2024-26606, CVE-2024-26608, CVE-2024-26610, CVE-2024-26611, CVE-2024-26612, CVE-2024-26614, CVE-2024-26615, CVE-2024-26616, CVE-2024-26617, CVE-2024-26618, CVE-2024-26619, CVE-2024-26620, CVE-2024-26621, CVE-2024-26625, CVE-2024-26626, CVE-2024-26627, CVE-2024-26629, CVE-2024-26630, CVE-2024-26631, CVE-2024-26632, CVE-2024-26633, CVE-2024-26634, CVE-2024-26635, CVE-2024-26636, CVE-2024-26637, CVE-2024-26638, CVE-2024-26639, CVE-2024-26640, CVE-2024-26641, CVE-2024-26643, CVE-2024-26644, CVE-2024-26645, CVE-2024-26649, CVE-2024-26652, CVE-2024-26653, CVE-2024-26657, CVE-2024-26660, CVE-2024-26663, CVE-2024-26664, CVE-2024-26665, CVE-2024-26666, CVE-2024-26667, CVE-2024-26668, CVE-2024-26670, CVE-2024-26671, CVE-2024-26673, CVE-2024-26674, CVE-2024-26675, CVE-2024-26676, CVE-2024-26678, CVE-2024-26679, CVE-2024-26681, CVE-2024-26682, CVE-2024-26683, CVE-2024-26684, CVE-2024-26685, CVE-2024-26689, CVE-2024-26690, CVE-2024-26692, CVE-2024-26693, CVE-2024-26694, CVE-2024-26695, CVE-2024-26696, CVE-2024-26697, CVE-2024-26698, CVE-2024-26702, CVE-2024-26703, CVE-2024-26704, CVE-2024-26705, CVE-2024-26707, CVE-2024-26708, CVE-2024-26709, CVE-2024-26710, CVE-2024-26711, CVE-2024-26712, CVE-2024-26715, CVE-2024-26716, CVE-2024-26717, CVE-2024-26720, CVE-2024-26721, CVE-2024-26722, CVE-2024-26723, CVE-2024-26724, CVE-2024-26725, CVE-2024-26727, CVE-2024-26728, CVE-2024-26729, CVE-2024-26730, CVE-2024-26731, CVE-2024-26732, CVE-2024-26733, CVE-2024-26734, CVE-2024-26735, CVE-2024-26736, CVE-2024-26737, CVE-2024-26741, CVE-2024-26742, CVE-2024-26743, CVE-2024-26744, CVE-2024-26746, CVE-2024-26747, CVE-2024-26748, CVE-2024-26749, CVE-2024-26750, CVE-2024-26751, CVE-2024-26752, CVE-2024-26753, CVE-2024-26754, CVE-2024-26755, CVE-2024-26760, CVE-2024-26761, CVE-2024-26762, CVE-2024-26763, CVE-2024-26764, CVE-2024-26766, CVE-2024-26769, CVE-2024-26771, CVE-2024-26772, CVE-2024-26773, CVE-2024-26774, CVE-2024-26776, CVE-2024-26777, CVE-2024-26778, CVE-2024-26779, CVE-2024-26780, CVE-2024-26781, CVE-2024-26783, CVE-2024-26785, CVE-2024-26786, CVE-2024-26792, CVE-2024-26794, CVE-2024-26796, CVE-2024-26799, CVE-2024-26800, CVE-2024-26807 and CVE-2024-26808

- ncurses: Fix CVE-2023-45918
- ofono: Fix CVE-2023-4233 and CVE-2023-4234
- openssl: Fix CVE-2024-4603
- util-linux: Fix CVE-2024-28085
- xserver-xorg: Fix CVE-2024-31082 and CVE-2024-31083

### **Fixes in Yocto-4.0.19**

- binutils: Rename CVE-2022-38126 patch to CVE-2022-35205
- bitbake: parse: Improve/fix cache invalidation via mtime
- build-appliance-image: Update to kirkstone head revision
- go-mod.bbclass: do not pack go mod cache
- dev-manual: update custom distribution section
- docs: poky.yaml.in: drop mesa/sdl from essential host packages

- docs: standards.md: align with master branch
- glibc: Update to latest on stable 2.35 branch (54a666dc5c...)
- go.bbclass: fix path to linker in native Go builds
- go.bbclass: Always pass interpreter to linker
- initscripts: Add custom mount args for /var/lib
- kernel.bbclass: check if directory exists before removing empty module directory
- libpciaccess: Remove duplicated license entry
- linux-yocto/5.15: cfg: remove obsolete CONFIG\_NFSD\_V3 option
- linux-yocto/5.15: update to v5.15.157
- migration-notes: add release notes for 4.0.18
- poky.conf: bump version for 4.0.19
- ppp: Add RSA-MD in *LICENSE*
- python3: Upgrade to 3.10.14
- ref-manual: update releases.svg
- ref-manual: variables: Update default *INHERIT\_DISTRO* value
- rootfs-postcommands.bbclass: Only set DROPBEAR\_RSAKEY\_DIR once
- systemd-systemctl: Fix WantedBy processing

### Known Issues in Yocto-4.0.19

- N/A

### Contributors to Yocto-4.0.19

- Alexander Kanavin
- Archana Polampalli
- Bhabu Bindu
- Bob Henz
- Bruce Ashfield
- Colin McAllister
- Dmitry Baryshkov
- Geoff Parker
- Heiko Thole
- Joerg Vehlowl
- Lee Chee Yang
- Michael Glembotzki

- Michael Opdenacker
- Paul Eggleton
- Peter Marko
- Poonam Jadhav
- Richard Purdie
- Soumya Sambu
- Stefan Herbrechtsmeier
- Steve Sakoman
- Vijay Anusuri
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.19

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.19](#)
- Git Revision: [e139e9d0ce343ba77a09601a976c92acd562c9df](#)
- Release Artefact: [poky-e139e9d0ce343ba77a09601a976c92acd562c9df](#)
- sha: [3e568af60ee599e262a359b50446c6cbe239481d8be2ee55403bda497735d636](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.19/poky-e139e9d0ce343ba77a09601a976c92acd562c9df.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.19/poky-e139e9d0ce343ba77a09601a976c92acd562c9df.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.19](#)
- Git Revision: [ab2649ef6c83f0ae7cac554a72e6bea4dcda0e99](#)
- Release Artefact: [oecore-ab2649ef6c83f0ae7cac554a72e6bea4dcda0e99](#)
- sha: [abc7601650651a2d2260f7e7e9e2e0709f25233148d66cb2d9481775b7b59a0c](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.19/oecore-ab2649ef6c83f0ae7cac554a72e6bea4dcda0e99.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.19/oecore-ab2649ef6c83f0ae7cac554a72e6bea4dcda0e99.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>



- Branch: `kirkstone`
- Tag: `yocto-4.0.19`
- Git Revision: `f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- Release Artefact: `meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- sha: `7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.19/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.19/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.19`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.19/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.19/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.19`
- Git Revision: `5a90927f31c4f9fccbe5d9d07d08e6e69485baa8`
- Release Artefact: `bitbake-5a90927f31c4f9fccbe5d9d07d08e6e69485baa8`
- sha: `e64b7f747718d10565d733057a8e6ee592c6b64983c7ffe623f9315ad35b6e0c`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.19/bitbake-5a90927f31c4f9fccbe5d9d07d08e6e69485baa8.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.19/bitbake-5a90927f31c4f9fccbe5d9d07d08e6e69485baa8.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.19`
- Git Revision: `78b8d5b18274a41ffec43ca4e136abc717585f6d`

## 17.11.22 Release notes for Yocto-4.0.20 (Kirkstone)

### Security Fixes in Yocto-4.0.20

- acpica: Fix [CVE-2024-24856](#)
- glib-2.0: Fix [CVE-2024-34397](#)
- gstreamer1.0-plugins-base: Fix [CVE-2024-4453](#)
- libxml2: Fix [CVE-2024-34459](#)
- openssh: fix [CVE-2024-6387](#)
- openssl: Fix [CVE-2024-4741](#) and [CVE-2024-5535](#)
- ruby: fix [CVE-2024-27280](#)
- wget: Fix for [CVE-2024-38428](#)

### Fixes in Yocto-4.0.20

- bitbake: tests/fetch: Tweak test to match upstream repo url change Upstream changed their urls, update our test to match.
- build-appliance-image: Update to kirkstone head revision
- glibc-tests: Add missing bash ptest dependency
- glibc-tests: correctly pull in the actual tests when installing -ptest package
- glibc: stable 2.35 branch updates
- gobject-introspection: Do not hardcode objdump name
- linuxloader: add -armhf on arm only for *TARGET\_FPU* 'hard'
- man-pages: add an alternative link name for crypt\_r.3
- man-pages: remove conflict pages
- migration-guides: add release notes for 4.0.19
- openssl: Upgrade 3.0.13 -> 3.0.14
- poky.conf: bump version for 4.0.20

### Known Issues in Yocto-4.0.20

- N/A

### Contributors to Yocto-4.0.20

- Archana Polampalli
- Changqing Li
- Deepthi Hemraj
- Jonas Gorski

- Jose Quaresma
- Khem Raj
- Lee Chee Yang
- Peter Marko
- Poonam Jadhav
- Siddharth Doshi
- Steve Sakoman
- Thomas Perrot
- Vijay Anusuri
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.20

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.20](#)
- Git Revision: [6bd3969d32730538608e680653e032e66958fe84](#)
- Release Artefact: [poky-6bd3969d32730538608e680653e032e66958fe84](#)
- sha: [b7ef1bd5ba1af257c4eb07a59b51d69e147723aea010eb2da99ea30dcbbbe2d9](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.20/poky-6bd3969d32730538608e680653e032e66958fe84.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.20/poky-6bd3969d32730538608e680653e032e66958fe84.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.20](#)
- Git Revision: [5d97b0576e98a2cf402abab1a1edcab223545d87](#)
- Release Artefact: [oecore-5d97b0576e98a2cf402abab1a1edcab223545d87](#)
- sha: [4064a32b8ff1ad8a98aa15e75b27585d2b27236c8cdfa4a28af6d6fef99b93c0](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.20/oecore-5d97b0576e98a2cf402abab1a1edcab223545d87.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.20/oecore-5d97b0576e98a2cf402abab1a1edcab223545d87.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>

- Branch: [kirkstone](#)
- Tag: [yocto-4.0.20](#)
- Git Revision: [f6b38ce3c90e1600d41c2ebb41e152936a0357d7](#)
- Release Artefact: [meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7](#)
- sha: [7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.20/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.20/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.20](#)
- Git Revision: [d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- Release Artefact: [meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- sha: [c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.20/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.20/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.0](#)
- Tag: [yocto-4.0.20](#)
- Git Revision: [734b0ea3dfe45eb16ee60f0c2c388e22af4040e0](#)
- Release Artefact: [bitbake-734b0ea3dfe45eb16ee60f0c2c388e22af4040e0](#)
- sha: [99f4c6786fec790fd6c4577b5dea3c97c580cc4815bd409ce554a68ee99b0180](#)
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.20/bitbake-734b0ea3dfe45eb16ee60f0c2c388e22af4040e0.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.20/bitbake-734b0ea3dfe45eb16ee60f0c2c388e22af4040e0.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.20](#)
- Git Revision: [b15b1d369edf33cd91232fefa0278e7e89653a01](#)

## 17.11.23 Release notes for Yocto-4.0.21 (Kirkstone)

### Security Fixes in Yocto-4.0.21

- bind: Fix CVE-2024-4076, CVE-2024-1737, CVE-2024-0760 and CVE-2024-1975
- apr: Fix CVE-2023-49582
- busybox: Fix CVE-2023-42363, CVE-2023-42364, CVE-2023-42365, CVE-2023-42366 and CVE-2021-42380
- curl: Ignore CVE-2024-32928
- curl: Fix CVE-2024-7264
- ghostscript: Fix CVE-2024-29506, CVE-2024-29509 and CVE-2024-29511
- go: Fix CVE-2024-24789 and CVE-2024-24791
- gtk+3: Fix CVE-2024-6655
- libarchive: Ignore CVE-2024-37407
- libyaml: Ignore CVE-2024-35325, CVE-2024-35326 and CVE-2024-35328
- linux-yocto/5.15: Fix CVE-2022-48772, CVE-2024-35972, CVE-2024-35984, CVE-2024-35990, CVE-2024-35997, CVE-2024-36008, CVE-2024-36270, CVE-2024-36489, CVE-2024-36897, CVE-2024-36938, CVE-2024-36965, CVE-2024-36967, CVE-2024-36969, CVE-2024-36971, CVE-2024-36978, CVE-2024-38546, CVE-2024-38547, CVE-2024-38549, CVE-2024-38552, CVE-2024-38555, CVE-2024-38571, CVE-2024-38583, CVE-2024-38591, CVE-2024-38597, CVE-2024-38598, CVE-2024-38600, CVE-2024-38627, CVE-2024-38633, CVE-2024-38661, CVE-2024-38662, CVE-2024-38780, CVE-2024-39277, CVE-2024-39292, CVE-2024-39301, CVE-2024-39466, CVE-2024-39468, CVE-2024-39471, CVE-2024-39475, CVE-2024-39476, CVE-2024-39480, CVE-2024-39482, CVE-2024-39484, CVE-2024-39487, CVE-2024-39489, CVE-2024-39493, CVE-2024-39495, CVE-2024-39506, CVE-2024-40902, CVE-2024-40911, CVE-2024-40912, CVE-2024-40932, CVE-2024-40934, CVE-2024-40954, CVE-2024-40956, CVE-2024-40957, CVE-2024-40958, CVE-2024-40959, CVE-2024-40960, CVE-2024-40961, CVE-2024-40967, CVE-2024-40970, CVE-2024-40980, CVE-2024-40981, CVE-2024-40994, CVE-2024-40995, CVE-2024-41000, CVE-2024-41002, CVE-2024-41006, CVE-2024-41007, CVE-2024-41046, CVE-2024-41049, CVE-2024-41055, CVE-2024-41064, CVE-2024-41070, CVE-2024-41073, CVE-2024-41087, CVE-2024-41089, CVE-2024-41092, CVE-2024-41093, CVE-2024-41095, CVE-2024-41097, CVE-2024-42068, CVE-2024-42070, CVE-2024-42076, CVE-2024-42077, CVE-2024-42080, CVE-2024-42082, CVE-2024-42085, CVE-2024-42090, CVE-2024-42093, CVE-2024-42094, CVE-2024-42101, CVE-2024-42102, CVE-2024-42104, CVE-2024-42109, CVE-2024-42140, CVE-2024-42148, CVE-2024-42152, CVE-2024-42153, CVE-2024-42154, CVE-2024-42157, CVE-2024-42161, CVE-2024-42223, CVE-2024-42224, CVE-2024-42225, CVE-2024-42229, CVE-2024-42232, CVE-2024-42236, CVE-2024-42244 and CVE-2024-42247
- llvm: Fix CVE-2023-46049 and CVE-2024-31852
- ofono: fix CVE-2023-2794
- orc: Fix CVE-2024-40897
- python3-certifi: Fix CVE-2024-39689

- python3-jinja2: Fix [CVE-2024-34064](#)
- python3: Fix [CVE-2024-8088](#)
- qemu: Fix [CVE-2024-7409](#)
- ruby: Fix for [CVE-2024-27282](#)
- tiff: Fix [CVE-2024-7006](#)
- vim: Fix [CVE-2024-22667](#), [CVE-2024-41957](#), [CVE-2024-41965](#) and [CVE-2024-43374](#)
- wpa-suplicant: Fix [CVE-2023-52160](#)

### Fixes in Yocto-4.0.21

- apr: upgrade to 1.7.5
- bind: Upgrade to 9.18.28
- bitbake: data\_smart: Improve performance for VariableHistory
- build-appliance-image: Update to kirkstone head revision
- cryptodev-module: Fix build for linux 5.10.220
- gcc-runtime: remove bashism
- grub: fs/fat: Don't error when mtime is 0
- image\_types.bbclass: Use --force also with lz4,lzop
- libsoup: fix compile error on centos7
- linux-yocto/5.15: upgrade to v5.15.164
- lttnng-modules: Upgrade to 2.13.14
- migration-guide: add release notes for 4.0.20
- orc: upgrade to 0.4.39
- poky.conf: bump version for 4.0.21
- python3-jinja2: upgrade to 3.1.4
- python3-pycryptodome(x): use python\_setuptools\_build\_meta build class
- python3: add PACKAGECONFIG[editline]
- ref-manual: fix typo and move [SYSROOT\\_DIRS](#) example
- sqlite3: CVE\_ID correction for [CVE-2023-7104](#) as patched
- sqlite3: Rename patch for [CVE-2022-35737](#)
- uboot-sign: Fix index error in concat\_dtb\_helper() with multiple configs
- vim: upgrade to 9.1.0682
- wireless-regdb: upgrade to 2024.07.04

### Known Issues in Yocto-4.0.21

- N/A

### Contributors to Yocto-4.0.21

- Archana Polampalli
- Ashish Sharma
- Bruce Ashfield
- Deepthi Hemraj
- Divya Chellam
- Florian Amstutz
- Guocai He
- Hitendra Prajapati
- Hugo SIMELIERE
- Lee Chee Yang
- Leon Anavi
- Matthias Pritschet
- Ming Liu
- Niko Mauno
- Peter Marko
- Robert Yang
- Rohini Sangam
- Ross Burton
- Siddharth Doshi
- Soumya Sambu
- Steve Sakoman
- Vijay Anusuri
- Vrushti Dabhi
- Wang Mingyu
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.21

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.21`
- Git Revision: `4cdc553814640851cce85f84ee9c0b58646cd33b`
- Release Artefact: `poky-4cdc553814640851cce85f84ee9c0b58646cd33b`
- sha: `460e3a4ede491a9b66c5d262cd9498d5bcca1f2d880885342b08dc32b967f33d`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.21/poky-4cdc553814640851cce85f84ee9c0b58646cd33b.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.21/poky-4cdc553814640851cce85f84ee9c0b58646cd33b.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.21`
- Git Revision: `c40a3fec49942ac6d25ba33e57e801a550e252c9`
- Release Artefact: `oecore-c40a3fec49942ac6d25ba33e57e801a550e252c9`
- sha: `afc2aaf312f9fb2590ae006615557ec605c98eff42bc380a1b2d6e39cfd8930`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.21/oecore-c40a3fec49942ac6d25ba33e57e801a550e252c9.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.21/oecore-c40a3fec49942ac6d25ba33e57e801a550e252c9.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.21`
- Git Revision: `f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- Release Artefact: `meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7`
- sha: `7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.21/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.21/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`



- Tag: `yocto-4.0.21`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.21/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.21/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.21`
- Git Revision: `ec2a99a077da9aa0e99e8b05e0c65dcbd45864b1`
- Release Artefact: `bitbake-ec2a99a077da9aa0e99e8b05e0c65dcbd45864b1`
- sha: `1cb102f4c8dbd067f0262072e4e629ec7cb423103111ccdde75a09fcb8f55e5f`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.21/bitbake-ec2a99a077da9aa0e99e8b05e0c65dcbd45864b1.tar.bz2>    <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.21/bitbake-ec2a99a077da9aa0e99e8b05e0c65dcbd45864b1.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.21`
- Git Revision: `512025edd9b3b6b8d0938b35bb6188c9f3b7f17d`

## 17.11.24 Release notes for Yocto-4.0.22 (Kirkstone)

### Security Fixes in Yocto-4.0.22

- cups: Fix CVE-2024-35235 and CVE-2024-47175
- curl: Fix CVE-2024-8096
- expat: Fix CVE-2024-45490, CVE-2024-45491 and CVE-2024-45492
- gnupg: Ignore CVE-2022-3219
- libpcap: Fix CVE-2023-7256 and CVE-2024-8006
- linux-yocto/5.10: Fix CVE-2022-48772, CVE-2023-52434, CVE-2023-52447, CVE-2023-52458, CVE-2024-0841, CVE-2024-26601, CVE-2024-26882, CVE-2024-26883, CVE-2024-26884, CVE-2024-26885, CVE-2024-26898, CVE-2024-26901, CVE-2024-26903, CVE-2024-26907, CVE-2024-26934, CVE-2024-26978, CVE-2024-27013, CVE-2024-27020, CVE-2024-35972, CVE-2024-35978, CVE-2024-35982,

CVE-2024-35984, CVE-2024-35990, CVE-2024-35997, CVE-2024-36008, CVE-2024-36270, CVE-2024-36489, CVE-2024-36902, CVE-2024-36971, CVE-2024-36978, CVE-2024-38546, CVE-2024-38547, CVE-2024-38549, CVE-2024-38552, CVE-2024-38555, CVE-2024-38583, CVE-2024-38590, CVE-2024-38597, CVE-2024-38598, CVE-2024-38627, CVE-2024-38633, CVE-2024-38661, CVE-2024-38662, CVE-2024-38780, CVE-2024-39292, CVE-2024-39301, CVE-2024-39468, CVE-2024-39471, CVE-2024-39475, CVE-2024-39476, CVE-2024-39480, CVE-2024-39482, CVE-2024-39484, CVE-2024-39487, CVE-2024-39489, CVE-2024-39495, CVE-2024-39506, CVE-2024-40902, CVE-2024-40904, CVE-2024-40905, CVE-2024-40912, CVE-2024-40932, CVE-2024-40934, CVE-2024-40958, CVE-2024-40959, CVE-2024-40960, CVE-2024-40961, CVE-2024-40980, CVE-2024-40981, CVE-2024-40995, CVE-2024-41000, CVE-2024-41006, CVE-2024-41007, CVE-2024-41012, CVE-2024-41040, CVE-2024-41046, CVE-2024-41049, CVE-2024-41059, CVE-2024-41063, CVE-2024-41064, CVE-2024-41070, CVE-2024-41087, CVE-2024-41089, CVE-2024-41092, CVE-2024-41095, CVE-2024-41097, CVE-2024-42070, CVE-2024-42076, CVE-2024-42077, CVE-2024-42082, CVE-2024-42090, CVE-2024-42093, CVE-2024-42094, CVE-2024-42101, CVE-2024-42102, CVE-2024-42104, CVE-2024-42131, CVE-2024-42137, CVE-2024-42148, CVE-2024-42152, CVE-2024-42153, CVE-2024-42154, CVE-2024-42157, CVE-2024-42161, CVE-2024-42223, CVE-2024-42224, CVE-2024-42229, CVE-2024-42232, CVE-2024-42236, CVE-2024-42244 and CVE-2024-42247

- **linux-yocto/5.15:** Fix CVE-2023-52889, CVE-2024-41011, CVE-2024-42114, CVE-2024-42259, CVE-2024-42271, CVE-2024-42272, CVE-2024-42277, CVE-2024-42280, CVE-2024-42283, CVE-2024-42284, CVE-2024-42285, CVE-2024-42286, CVE-2024-42287, CVE-2024-42288, CVE-2024-42289, CVE-2024-42301, CVE-2024-42302, CVE-2024-42309, CVE-2024-42310, CVE-2024-42311, CVE-2024-42313, CVE-2024-43817, CVE-2024-43828, CVE-2024-43854, CVE-2024-43856, CVE-2024-43858, CVE-2024-43860, CVE-2024-43861, CVE-2024-43863, CVE-2024-43871, CVE-2024-43873, CVE-2024-43882, CVE-2024-43889, CVE-2024-43890, CVE-2024-43893, CVE-2024-43894, CVE-2024-43902, CVE-2024-43907, CVE-2024-43908, CVE-2024-43909, CVE-2024-43914, CVE-2024-44934, CVE-2024-44935, CVE-2024-44944, CVE-2024-44947, CVE-2024-44952, CVE-2024-44954, CVE-2024-44958, CVE-2024-44960, CVE-2024-44965, CVE-2024-44966, CVE-2024-44969, CVE-2024-44971, CVE-2024-44982, CVE-2024-44983, CVE-2024-44985, CVE-2024-44986, CVE-2024-44987, CVE-2024-44988, CVE-2024-44989, CVE-2024-44990, CVE-2024-44995, CVE-2024-44998, CVE-2024-44999, CVE-2024-45003, CVE-2024-45006, CVE-2024-45011, CVE-2024-45016, CVE-2024-45018, CVE-2024-45021, CVE-2024-45025, CVE-2024-45026, CVE-2024-45028, CVE-2024-46673, CVE-2024-46674, CVE-2024-46675, CVE-2024-46676, CVE-2024-46677, CVE-2024-46679, CVE-2024-46685, CVE-2024-46689, CVE-2024-46702 and CVE-2024-46707
- **openssl:** Fix CVE-2024-6119
- **procps:** Fix CVE-2023-4016
- **python3:** Fix CVE-2023-27043, CVE-2024-4030, CVE-2024-4032, CVE-2024-6923, CVE-2024-6232, CVE-2024-7592 and CVE-2024-8088
- **qemu:** Fix CVE-2024-4467
- **rust:** Ignore CVE-2024-43402
- **webkitgtk:** Fix CVE-2024-40779
- **wpa-suplicant:** Ignore CVE-2024-5290

- wpa-supPLICant: Fix [CVE-2024-3596](#)

## Fixes in Yocto-4.0.22

- bintuils: stable 2.38 branch update
- bitbake: fetch2/wget: Canonicalize [DL\\_DIR](#) paths for wget2 compatibility
- bitbake: fetch/wget: Move files into place atomically
- bitbake: hashserv: tests: Omit client in slow server start test
- bitbake: tests/fetch: Tweak to work on Fedora40
- bitbake: wget: Make wget --passive-ftp option conditional on ftp/ftps
- build-appliance-image: Update to kirkstone head revision
- buildhistory: Fix intermittent package file list creation
- buildhistory: Restoring files from preserve list
- buildhistory: Simplify intercept call sites and drop SSTATEPOSTINSTFUNC usage
- busybox: Fix cut with "-s" flag
- cdrtools-native: fix build with gcc-14
- curl: free old conn better on reuse
- cve-exclusion: Drop the version comparision/warning
- dejagnu: Fix [LICENSE](#) (change to GPL-3.0-only)
- doc/features: remove duplicate word in distribution feature ext2
- gcc: upgrade to v11.5
- gcr: Fix [LICENSE](#) (change to LGPL-2.0-only)
- glibc: stable 2.35 branch updates
- install-buildtools: fix "test installation" step
- install-buildtools: remove md5 checksum validation
- install-buildtools: support buildtools-make-tarball and update to 4.1
- iw: Fix [LICENSE](#) (change to ISC)
- kmscube: Add patch to fix -int-conversion build error
- lib/oeqa: rename assertRaisesRegexp to assertRaisesRegex
- libedit: Make docs generation deterministic
- linux-yocto/5.10: fix NFSV3 config warning
- linux-yocto/5.10: remove obsolete options
- linux-yocto/5.10: update to v5.10.223
- linux-yocto/5.15: update to v5.15.166

- meta-world-pkgdata: Inherit nopackages
- migration-guide: add release notes for 4.0.21
- openssl: Upgrade to 3.0.15
- poky.conf: bump version for 4.0.22
- populate\_sdk\_base: inherit nopackages
- python3: Upgrade to 3.10.15
- ruby: Make docs generation deterministic
- runqemu: keep generating tap devices
- scripts/install-buildtools: Update to 4.0.21
- selftest/runtime\_test/virgl: Disable for all fedora
- testexport: fallback for empty *IMAGE\_LINK\_NAME*
- testimage: fallback for empty *IMAGE\_LINK\_NAME*
- tiff: Fix *LICENSE* (change to libtiff)
- udev-extraconf: Add collect flag to mount
- unzip: Fix *LICENSE* (change to Info-ZIP)
- valgrind: disable avx\_estimate\_insn.vgtest
- wpa-suplicant: Patch security advisory 2024-2
- yocto-uninative: Update to 4.5 for gcc 14
- yocto-uninative: Update to 4.6 for glibc 2.40
- zip: Fix *LICENSE* (change to Info-ZIP)
- zstd: fix *LICENSE* statement (change to "BSD-3-Clause | GPL-2.0-only")

### Known Issues in Yocto-4.0.22

- oeqa/runtime: the beaglebone-yocto target fails the parselogs runtime test due to unexpected kernel error messages in the log (see [bug 15624](#) on Bugzilla).

### Contributors to Yocto-4.0.22

- Aleksandar Nikolic
- Alexandre Belloni
- Archana Polampalli
- Bruce Ashfield
- Colin McAllister
- Deepthi Hemraj
- Divya Chellam

- Hitendra Prajapati
- Hugo SIMELIERE
- Jinfeng Wang
- Joshua Watt
- Jörg Sommer
- Konrad Weihmann
- Lee Chee Yang
- Martin Jansa
- Massimiliano Minella
- Michael Halstead
- Mingli Yu
- Niko Mauno
- Paul Eggleton
- Pedro Ferreira
- Peter Marko
- Purushottam Choudhary
- Richard Purdie
- Rob Woolley
- Rohini Sangam
- Ross Burton
- Rudolf J Streif
- Siddharth Doshi
- Steve Sakoman
- Vijay Anusuri
- Vivek Kumbhar

## Repositories / Downloads for Yocto-4.0.22

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.22](#)
- Git Revision: [7e87dc422d972e0dc98372318fcdc63a76347d16](#)
- Release Artefact: [poky-7e87dc422d972e0dc98372318fcdc63a76347d16](#)

- sha: 5058e7b2474f8cb73c19e776ef58d9784321ef42109d5982747c8c432531239f
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.22/poky-7e87dc422d972e0dc98372318fcdc63a76347d16.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.22/poky-7e87dc422d972e0dc98372318fcdc63a76347d16.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: kirkstone
- Tag: yocto-4.0.22
- Git Revision: f09fca692f96c9c428e89c5ef53fbc92ac0c9bf
- Release Artefact: oecore-f09fca692f96c9c428e89c5ef53fbc92ac0c9bf
- sha: 378bcc840ba9fbf06a15fea1b5dacdd446f3ad4d85115d708e7bbb20629cdeb4
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.22/oecore-f09fca692f96c9c428e89c5ef53fbc92ac0c9bf.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.22/oecore-f09fca692f96c9c428e89c5ef53fbc92ac0c9bf.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.22
- Git Revision: f6b38ce3c90e1600d41c2ebb41e152936a0357d7
- Release Artefact: meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7
- sha: 7d57167c19077f4ab95623d55a24c2267a3a3fb5ed83688659b4c03586373b25
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.22/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.22/meta-mingw-f6b38ce3c90e1600d41c2ebb41e152936a0357d7.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.22
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.22/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.22/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.22
- Git Revision: [eb5c1ce6b1b8f33535ff7b9263ec7648044163ea](#)
- Release Artefact: [bitbake-eb5c1ce6b1b8f33535ff7b9263ec7648044163ea](#)
- sha: [473d3e9539160633f3de9d88cce69123f6c623e4c8ab35beb7875868564593cf](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-4.0.22/bitbake-eb5c1ce6b1b8f33535ff7b9263ec7648044163ea.tar.bz2> <http://mirrors.kernel.org/yocto/yocto/yocto-4.0.22/bitbake-eb5c1ce6b1b8f33535ff7b9263ec7648044163ea.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.22
- Git Revision: [2169a52a24ebd1906039c42632bae6c4285a3aca](#)

### 17.11.25 Release notes for Yocto-4.0.23 (Kirkstone)

#### Security Fixes in Yocto-4.0.23

- curl: Fix CVE-2024-9681
- expat: Fix CVE-2024-50602
- gcc: Ignore CVE-2023-4039
- ghostscript: Fix CVE-2023-46361 and CVE-2024-29508
- gstreamer1.0: Ignore CVE-2024-0444
- libarchive: Fix CVE-2024-48957 and CVE-2024-48958
- openssl: Fix CVE-2024-9143
- orc: Fix CVE-2024-40897
- python3: Ignore CVE-2023-27043, CVE-2024-6232 and CVE-2024-7592
- qemu: Fix CVE-2023-3019
- vim: Fix CVE-2024-43790, CVE-2024-43802, CVE-2024-45306 and CVE-2024-47814
- zstd: Fix CVE-2022-4899

#### Fixes in Yocto-4.0.23

- at-spi2-core: backport a patch to fix build with gcc-14 on host
- bitbake: bitbake: doc/user-manual: Update the BB\_HASHSERVE\_UPSTREAM
- bitbake: codeparser: Fix handling of string AST nodes with older Python versions

- bitbake: fetch2/git: Use quote from shlex, not pipes
- bitbake: git-sm: Add `call_process_submodules()` to remove duplicated code
- bitbake: git-sm: Remove downloads/tmpdir when failed
- bitbake: tests/fetch: Use our own mirror of mobile-broadband-provider to decouple from gnome gitlab
- bitbake: tests/fetch: Use our own mirror of sysprof to decouple from gnome gitlab
- bmap-tools: update [HOMEPAGE](#) and [SRC\\_URI](#)
- build-appliance-image: Update to kirkstone head revision
- cmake: Fix sporadic issues when determining compiler internals
- cracklib: Modify patch to compile with GCC 14
- cve-check: add CVSS vector string to CVE database and reports
- cve-check: add support for cvss v4.0
- cve\_check: Use a local copy of the database during builds
- dev-manual: document how to provide confs from layer.conf
- documentation: Makefile: add SPHINXLINTDOCS to specify subset to sphinx-lint
- documentation: Makefile: fix epub and latexpdf targets
- documentation: README: add instruction to run Vale on a subset
- documentation: brief-yoctoprojectqs: update BB\_HASHSERVE\_UPSTREAM for new infrastructure
- documentation: conf.py: add a bitbake\_git extlink
- documentation: rename :cve: role to :cve\_nist:
- documentation: styles: vocabularies: Yocto: add sstate
- documnetation: contributor-guide: Remove duplicated words
- gcc: restore a patch for Neoverse N2 core
- glib-2.0: patch regression of [CVE-2023-32665](#)
- kmscube: create\_framebuffer: backport modifier fix
- libffi: backport a fix to build libffi-native with gcc-14
- linux-firmware: Upgrade to 20240909
- local.conf.sample: update BB\_HASHSERVE\_UPSTREAM for new infrastructure
- migration-guide: add release notes for 4.0.22
- migration-guide: release-notes-4.0: update BB\_HASHSERVE\_UPSTREAM for new infrastructure
- nativesdk-intercept: Fix bad intercept chgrp/chown logic
- orc: Upgrade to 0.4.40
- overlaysfs-etc: add option to skip creation of mount dirs



- overview-manual: concepts: add details on package splitting
- package: Switch debug source handling to use prefix map
- patch.py: Use shlex instead of deprecated pipe
- poky.conf: bump version for 4.0.23
- pseudo: Disable LFS on 32bit arches
- pseudo: Fix envp bug and add posix\_spawn wrapper
- pseudo: Fix to work with glibc 2.40
- pseudo: Switch back to the master branch
- pseudo: Update to include logic fix
- pseudo: Update to include open symlink handling bugfix
- pseudo: Update to pull in fchmodat fix
- pseudo: Update to pull in fd leak fix
- pseudo: Update to pull in gcc14 fix and missing statvfs64 intercept
- pseudo: Update to pull in linux-libc-headers race fix
- pseudo: Update to pull in python 3.12+ fix
- pseudo: Update to pull in syncfs probe fix
- ref-manual: add description for the "sysroot" term
- ref-manual: add missing CVE\_CHECK manifest variables
- ref-manual: add missing *EXTERNAL\_KERNEL\_DEVICETREE* variable
- ref-manual: add missing *OPKGBUILDCMD* variable
- ref-manual: devtool-reference: document missing commands
- ref-manual: devtool-reference: refresh example outputs
- ref-manual: introduce *CVE\_CHECK\_REPORT\_PATCHED* variable
- ref-manual: release-process: add a reference to the doc's release
- ref-manual: release-process: refresh the current LTS releases
- ref-manual: release-process: update releases.svg
- ref-manual: release-process: update releases.svg with month after "Current"
- ref-manual: structure.rst: document missing tmp/ dirs
- ref-manual: variables: add *SIGGEN\_LOCKEDSIGS\** variables
- syslinux: Disable error on implicit-function-declaration
- util-linux: Define pidfd\_\* function signatures
- vala: add -Wno-error=incompatible-pointer-types work around

- vim: Upgrade to 9.1.0764
- xmlto: backport a patch to fix build with gcc-14 on host
- zip: Fix build with gcc-14
- zip: Make configure checks to be more robust

### **Known Issues in Yocto-4.0.23**

-N/A

### **Contributors to Yocto-4.0.23**

- Aleksandar Nikolic
- Alexandre Belloni
- Antoine Lubineau
- Antonin Godard
- Archana Polampalli
- Ashish Sharma
- Baruch Siach
- Eilís 'pidge' Ní Fhlannagáin
- Jose Quaresma
- Julien Stephan
- Khem Raj
- Lee Chee Yang
- Macpaul Lin
- Martin Jansa
- Michael Opdenacker
- Ola x Nilsson
- Peter Marko
- Philip Lorenz
- Randolph Sapp
- Richard Purdie
- Robert Yang
- Rohini Sangam
- Ruiqiang Hao
- Siddharth Doshi
- Steve Sakoman

- Talel BELHAJSALEM
- Wang Mingyu
- Yogita Urade
- Zoltan Boszormenyi

## Repositories / Downloads for Yocto-4.0.23

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.23`
- Git Revision: `8e092852b63e998d990b8f8e1aa91297dec4430f`
- Release Artefact: `poky-8e092852b63e998d990b8f8e1aa91297dec4430f`
- sha: `339d34d8432070dac948449e732ebf06a888eeb27ff548958b2395c9446b029d`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.23/poky-8e092852b63e998d990b8f8e1aa91297dec4430f.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.23/poky-8e092852b63e998d990b8f8e1aa91297dec4430f.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.23`
- Git Revision: `fb45c5cf8c2b663af293acb069d446610f77ff1a`
- Release Artefact: `oecore-fb45c5cf8c2b663af293acb069d446610f77ff1a`
- sha: `1d394370ea7d43fb885ab8a952d6d1e43f1a850745a5152d5ead5565a283a0f5`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.23/oecore-fb45c5cf8c2b663af293acb069d446610f77ff1a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.23/oecore-fb45c5cf8c2b663af293acb069d446610f77ff1a.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.23`
- Git Revision: `87c22abb1f11be430caf4372e6b833dc7d77564e`
- Release Artefact: `meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e`
- sha: `f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8`

- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.23/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.23/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.23
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.23/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.23/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.23
- Git Revision: fb73c495c45d1d4107cfd60b67a5b4f11a99647b
- Release Artefact: bitbake-fb73c495c45d1d4107cfd60b67a5b4f11a99647b
- sha: 5cd271299951f25912a2e8d4de6d8769a4c0bb3bbcf90815be41f23fd299a0b
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.23/bitbake-fb73c495c45d1d4107cfd60b67a5b4f11a99647b.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.23/bitbake-fb73c495c45d1d4107cfd60b67a5b4f11a99647b.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.23
- Git Revision: TBD

## 17.11.26 Release notes for Yocto-4.0.24 (Kirkstone)

### Security Fixes in Yocto-4.0.24

- coreutils: Fix CVE-2024-0684
- cpio: Ignore CVE-2023-7216
- diffoscope: Fix CVE-2024-25711

- **ffmpeg:** fix CVE-2023-47342, CVE-2023-50007, CVE-2023-50008, CVE-2023-51793, CVE-2023-51794, CVE-2023-51796, CVE-2023-51798, CVE-2024-7055, CVE-2024-31578, CVE-2024-31582, CVE-2024-32230, CVE-2024-35366, CVE-2024-35367 and CVE-2024-35368
- **ghostscript:** Fix CVE-2024-46951, CVE-2024-46952, CVE-2024-46953, CVE-2024-46955 and CVE-2024-46956
- **ghostscript:** Ignore CVE-2024-46954
- **glib-2.0:** Fix CVE-2024-52533
- **gnupg:** Ignore CVE-2022-3515
- **grub:** Ignore CVE-2024-1048 and CVE-2023-4001
- **gststreamer1.0:** Ignore CVE-2023-40474, CVE-2023-40475, CVE-2023-40476, CVE-2023-44429, CVE-2023-44446, CVE-2023-50186 and CVE-2024-0444
- **gststreamer1.0-plugins-base:** Fix CVE-2024-47538, CVE-2024-47541, CVE-2024-47542, CVE-2024-47600, CVE-2024-47607, CVE-2024-47615 and CVE-2024-47835
- **gststreamer1.0-plugins-good:** Fix CVE-2024-47537, CVE-2024-47539, CVE-2024-47540, CVE-2024-47543, CVE-2024-47544, CVE-2024-47545, CVE-2024-47546, CVE-2024-47596, CVE-2024-47597, CVE-2024-47598, CVE-2024-47599, CVE-2024-47601, CVE-2024-47602, CVE-2024-47603, CVE-2024-47606, CVE-2024-47613, CVE-2024-47774, CVE-2024-47775, CVE-2024-47776, CVE-2024-47777, CVE-2024-47778 and CVE-2024-47834
- **gststreamer1.0:** Fix CVE-2024-47606
- **libarchive:** Fix CVE-2024-20696
- **libpam:** Fix CVE-2024-10041
- **libstdl2:** Ignore CVE-2020-14409 and CVE-2020-14410
- **libsndfile1:** Fix CVE-2022-33065 and CVE-2024-50612
- **libsoup-2.4:** Fix CVE-2024-52530, CVE-2024-52531 and CVE-2024-52532
- **libsoup:** Fix CVE-2024-52530, CVE-2024-52531 and CVE-2024-52532
- **linux-yocto/5.10:** Fix CVE-2023-52889, CVE-2023-52917, CVE-2023-52918, CVE-2024-41011, CVE-2024-42259, CVE-2024-42271, CVE-2024-42272, CVE-2024-42280, CVE-2024-42283, CVE-2024-42284, CVE-2024-42285, CVE-2024-42286, CVE-2024-42287, CVE-2024-42288, CVE-2024-42289, CVE-2024-42301, CVE-2024-42302, CVE-2024-42309, CVE-2024-42310, CVE-2024-42311, CVE-2024-42313, CVE-2024-43828, CVE-2024-43856, CVE-2024-43858, CVE-2024-43860, CVE-2024-43861, CVE-2024-43871, CVE-2024-43882, CVE-2024-43889, CVE-2024-43890, CVE-2024-43893, CVE-2024-43894, CVE-2024-43907, CVE-2024-43908, CVE-2024-43914, CVE-2024-44935, CVE-2024-44944, CVE-2024-44947, CVE-2024-44954, CVE-2024-44960, CVE-2024-44965, CVE-2024-44969, CVE-2024-44971, CVE-2024-44987, CVE-2024-44988, CVE-2024-44989, CVE-2024-44990, CVE-2024-44995, CVE-2024-44998, CVE-2024-44999, CVE-2024-45003, CVE-2024-45006, CVE-2024-45016, CVE-2024-45018, CVE-2024-45021, CVE-2024-45025, CVE-2024-45026, CVE-2024-45028, CVE-2024-46673, CVE-2024-46674, CVE-2024-46675, CVE-2024-46676, CVE-2024-46677, CVE-2024-46679, CVE-2024-46685, CVE-2024-46689, CVE-2024-46702, CVE-2024-46707, CVE-2024-46714, CVE-2024-46719,

CVE-2024-46721, CVE-2024-46722, CVE-2024-46723, CVE-2024-46724, CVE-2024-46725, CVE-2024-46731, CVE-2024-46737, CVE-2024-46738, CVE-2024-46739, CVE-2024-46740, CVE-2024-46743, CVE-2024-46744, CVE-2024-46747, CVE-2024-46750, CVE-2024-46755, CVE-2024-46759, CVE-2024-46761, CVE-2024-46763, CVE-2024-46771, CVE-2024-46777, CVE-2024-46780, CVE-2024-46781, CVE-2024-46782, CVE-2024-46783, CVE-2024-46791, CVE-2024-46798, CVE-2024-46800, CVE-2024-46804, CVE-2024-46814, CVE-2024-46815, CVE-2024-46817, CVE-2024-46818, CVE-2024-46819, CVE-2024-46822, CVE-2024-46828, CVE-2024-46829, CVE-2024-46832, CVE-2024-46840, CVE-2024-46844, CVE-2024-47659, CVE-2024-47660, CVE-2024-47663, CVE-2024-47667, CVE-2024-47668, CVE-2024-47669, CVE-2024-47679, CVE-2024-47684, CVE-2024-47685, CVE-2024-47692, CVE-2024-47697, CVE-2024-47698, CVE-2024-47699, CVE-2024-47701, CVE-2024-47705, CVE-2024-47706, CVE-2024-47710, CVE-2024-47712, CVE-2024-47713, CVE-2024-47718, CVE-2024-47723, CVE-2024-47735, CVE-2024-47737, CVE-2024-47739, CVE-2024-47742, CVE-2024-47747, CVE-2024-47748, CVE-2024-47749, CVE-2024-47757, CVE-2024-49851, CVE-2024-49858, CVE-2024-49860, CVE-2024-49863, CVE-2024-49867, CVE-2024-49868, CVE-2024-49875, CVE-2024-49877, CVE-2024-49878, CVE-2024-49879, CVE-2024-49881, CVE-2024-49882, CVE-2024-49883, CVE-2024-49884, CVE-2024-49889, CVE-2024-49890, CVE-2024-49892, CVE-2024-49894, CVE-2024-49895, CVE-2024-49896, CVE-2024-49900, CVE-2024-49902, CVE-2024-49903, CVE-2024-49907, CVE-2024-49913, CVE-2024-49924, CVE-2024-49930, CVE-2024-49933, CVE-2024-49936, CVE-2024-49938, CVE-2024-49944, CVE-2024-49948, CVE-2024-49949, CVE-2024-49952, CVE-2024-49955, CVE-2024-49957, CVE-2024-49958, CVE-2024-49959, CVE-2024-49962, CVE-2024-49963, CVE-2024-49965, CVE-2024-49966, CVE-2024-49969, CVE-2024-49973, CVE-2024-49975, CVE-2024-49977, CVE-2024-49981, CVE-2024-49982, CVE-2024-49983, CVE-2024-49985, CVE-2024-49995, CVE-2024-49997, CVE-2024-50001, CVE-2024-50006, CVE-2024-50007, CVE-2024-50008, CVE-2024-50013, CVE-2024-50015, CVE-2024-50024, CVE-2024-50033, CVE-2024-50035, CVE-2024-50039, CVE-2024-50040, CVE-2024-50044, CVE-2024-50045, CVE-2024-50046, CVE-2024-50049, CVE-2024-50059, CVE-2024-50095, CVE-2024-50096, CVE-2024-50179, CVE-2024-50180, CVE-2024-50181, CVE-2024-50184 and CVE-2024-50188

- **linux-yocto/5.15:** Fix CVE-2022-48695, CVE-2023-52530, CVE-2023-52917, CVE-2024-45009, CVE-2024-46714, CVE-2024-46719, CVE-2024-46721, CVE-2024-46722, CVE-2024-46723, CVE-2024-46724, CVE-2024-46725, CVE-2024-46731, CVE-2024-46732, CVE-2024-46737, CVE-2024-46738, CVE-2024-46739, CVE-2024-46740, CVE-2024-46743, CVE-2024-46744, CVE-2024-46746, CVE-2024-46747, CVE-2024-46750, CVE-2024-46755, CVE-2024-46759, CVE-2024-46761, CVE-2024-46763, CVE-2024-46771, CVE-2024-46777, CVE-2024-46780, CVE-2024-46781, CVE-2024-46782, CVE-2024-46783, CVE-2024-46791, CVE-2024-46795, CVE-2024-46798, CVE-2024-46800, CVE-2024-46804, CVE-2024-46805, CVE-2024-46807, CVE-2024-46810, CVE-2024-46814, CVE-2024-46815, CVE-2024-46817, CVE-2024-46818, CVE-2024-46819, CVE-2024-46822, CVE-2024-46828, CVE-2024-46829, CVE-2024-46832, CVE-2024-46840, CVE-2024-46844, CVE-2024-47659, CVE-2024-47660, CVE-2024-47663, CVE-2024-47665, CVE-2024-47667, CVE-2024-47668, CVE-2024-47669, CVE-2024-47674, CVE-2024-47679, CVE-2024-47684, CVE-2024-47685, CVE-2024-47690, CVE-2024-47692, CVE-2024-47693, CVE-2024-47695, CVE-2024-47696, CVE-2024-47697, CVE-2024-47698, CVE-2024-47699, CVE-2024-47701, CVE-2024-47705, CVE-2024-47706, CVE-2024-47710, CVE-2024-47712, CVE-2024-47713, CVE-2024-47718, CVE-2024-47720, CVE-2024-47723, CVE-2024-47734, CVE-2024-47735, CVE-2024-47737, CVE-2024-47739, CVE-2024-47742, CVE-2024-47747, CVE-2024-47748, CVE-2024-47749, CVE-2024-47757, CVE-2024-49851, CVE-2024-49852, CVE-2024-49854, CVE-2024-49856, CVE-2024-49858, CVE-2024-49860, CVE-2024-49863, CVE-2024-49866, CVE-2024-49867, CVE-2024-

49868, CVE-2024-49871, CVE-2024-49875, CVE-2024-49877, CVE-2024-49878, CVE-2024-49879, CVE-2024-49881, CVE-2024-49882, CVE-2024-49883, CVE-2024-49884, CVE-2024-49886, CVE-2024-49889, CVE-2024-49890, CVE-2024-49892, CVE-2024-49894, CVE-2024-49895, CVE-2024-49896, CVE-2024-49900, CVE-2024-49902, CVE-2024-49903, CVE-2024-49907, CVE-2024-49913, CVE-2024-49924, CVE-2024-49927, CVE-2024-49930, CVE-2024-49933, CVE-2024-49935, CVE-2024-49936, CVE-2024-49938, CVE-2024-49944, CVE-2024-49946, CVE-2024-49948, CVE-2024-49949, CVE-2024-49952, CVE-2024-49954, CVE-2024-49955, CVE-2024-49957, CVE-2024-49958, CVE-2024-49959, CVE-2024-49962, CVE-2024-49963, CVE-2024-49965, CVE-2024-49966, CVE-2024-49969, CVE-2024-49973, CVE-2024-49975, CVE-2024-49977, CVE-2024-49981, CVE-2024-49982, CVE-2024-49983, CVE-2024-49985, CVE-2024-49995, CVE-2024-49997, CVE-2024-50000, CVE-2024-50001, CVE-2024-50002, CVE-2024-50003, CVE-2024-50006, CVE-2024-50007, CVE-2024-50008, CVE-2024-50013, CVE-2024-50015, CVE-2024-50019, CVE-2024-50024, CVE-2024-50031, CVE-2024-50033, CVE-2024-50035, CVE-2024-50038, CVE-2024-50039, CVE-2024-50040, CVE-2024-50041, CVE-2024-50044, CVE-2024-50045, CVE-2024-50046, CVE-2024-50049, CVE-2024-50059, CVE-2024-50062, CVE-2024-50074, CVE-2024-50082, CVE-2024-50083, CVE-2024-50093, CVE-2024-50095, CVE-2024-50096, CVE-2024-50099, CVE-2024-50101, CVE-2024-50103, CVE-2024-50110, CVE-2024-50115, CVE-2024-50116, CVE-2024-50117, CVE-2024-50127, CVE-2024-50128, CVE-2024-50131, CVE-2024-50134, CVE-2024-50141, CVE-2024-50142, CVE-2024-50143, CVE-2024-50148, CVE-2024-50150, CVE-2024-50151, CVE-2024-50153, CVE-2024-50154, CVE-2024-50156, CVE-2024-50160, CVE-2024-50162, CVE-2024-50163, CVE-2024-50167, CVE-2024-50168, CVE-2024-50171, CVE-2024-50179, CVE-2024-50180, CVE-2024-50181, CVE-2024-50182, CVE-2024-50184, CVE-2024-50185, CVE-2024-50186, CVE-2024-50188, CVE-2024-50189, CVE-2024-50191, CVE-2024-50192, CVE-2024-50193, CVE-2024-50194, CVE-2024-50195, CVE-2024-50196, CVE-2024-50198, CVE-2024-50201, CVE-2024-50202, CVE-2024-50205, CVE-2024-50208, CVE-2024-50209, CVE-2024-50229, CVE-2024-50230, CVE-2024-50232, CVE-2024-50233, CVE-2024-50234, CVE-2024-50236, CVE-2024-50237, CVE-2024-50244, CVE-2024-50245, CVE-2024-50247, CVE-2024-50251, CVE-2024-50257, CVE-2024-50259, CVE-2024-50262, CVE-2024-50264, CVE-2024-50265, CVE-2024-50267, CVE-2024-50268, CVE-2024-50269, CVE-2024-50273, CVE-2024-50278, CVE-2024-50279, CVE-2024-50282, CVE-2024-50287, CVE-2024-50292, CVE-2024-50296, CVE-2024-50299, CVE-2024-50301, CVE-2024-50302, CVE-2024-53052, CVE-2024-53055, CVE-2024-53057, CVE-2024-53058, CVE-2024-53059, CVE-2024-53060, CVE-2024-53061, CVE-2024-53063, CVE-2024-53066, CVE-2024-53088, CVE-2024-53096, CVE-2024-53101, CVE-2024-53103, CVE-2024-53145, CVE-2024-53146, CVE-2024-53150, CVE-2024-53151, CVE-2024-53155, CVE-2024-53156, CVE-2024-53157, CVE-2024-53165, CVE-2024-53171, CVE-2024-53173, CVE-2024-53226, CVE-2024-53227, CVE-2024-53237, CVE-2024-56567, CVE-2024-56572, CVE-2024-56574, CVE-2024-56578, CVE-2024-56581, CVE-2024-56593, CVE-2024-56600, CVE-2024-56601, CVE-2024-56602, CVE-2024-56603, CVE-2024-56605, CVE-2024-56606, CVE-2024-56614, CVE-2024-56622, CVE-2024-56623, CVE-2024-56629, CVE-2024-56634, CVE-2024-56640, CVE-2024-56642, CVE-2024-56643, CVE-2024-56648, CVE-2024-56650, CVE-2024-56659, CVE-2024-56662, CVE-2024-56670, CVE-2024-56688, CVE-2024-56694, CVE-2024-56704, CVE-2024-56708, CVE-2024-56720, CVE-2024-56723, CVE-2024-56724, CVE-2024-56726, CVE-2024-56728, CVE-2024-56739, CVE-2024-56741, CVE-2024-56745, CVE-2024-56746, CVE-2024-56747, CVE-2024-56748, CVE-2024-56754, CVE-2024-56756, CVE-2024-56770, CVE-2024-56774, CVE-2024-56776, CVE-2024-56777, CVE-2024-56778, CVE-2024-56779, CVE-2024-56780, CVE-2024-56781, CVE-2024-56785 and CVE-2024-56787

- ovmf: Fix CVE-2022-36763, CVE-2022-36764, CVE-2022-36765, CVE-2023-45229, CVE-2023-45230,

CVE-2023-45231, CVE-2023-45232, CVE-2023-45233, CVE-2023-45234, CVE-2023-45235, CVE-2023-45236, CVE-2023-45237, CVE-2024-1298 and CVE-2024-38796

- pixman: Ignore CVE-2023-37769
- python3: Fix CVE-2024-9287, CVE-2024-11168 and CVE-2024-50602
- python3-pip: Fix CVE-2023-5752
- python3-requests: Fix CVE-2024-35195
- python3-zipp: Fix CVE-2024-5569
- qemu: Fix CVE-2024-3446, CVE-2024-3447 and CVE-2024-6505
- qemu: Ignore CVE-2022-36648
- subversion: Fix CVE-2024-46901
- tiff: Fix CVE-2023-3164
- tiff: Ignore CVE-2023-2731
- webkitgtk: Fix CVE-2024-40776 and CVE-2024-40780
- xserver-xorg: Fix CVE-2024-9632
- xwayland: Fix CVE-2023-5380 and CVE-2024-0229

#### Fixes in Yocto-4.0.24

- base-passwd: Add the sgx group
- base-passwd: Regenerate the patches
- base-passwd: Update the status for two patches
- base-passwd: Update to 3.5.52
- base-passwd: add the wheel group
- base-passwd: fix patchreview warning
- bitbake: fetch2: use persist\_data context managers
- bitbake: fetch/wget: Increase timeout to 100s from 30s
- bitbake: persist\_data: close connection in SQLTable \_\_exit\_\_
- build-appliance-image: Update to kirkstone head revision
- builder: set *CVE\_PRODUCT*
- contributor-guide: submit-changes.rst: suggest to remove the git signature
- cve-update-nvd2-native: Tweak to work better with NFS *DL\_DIR*
- dbus: disable assertions and enable only modular tests
- do\_package/ssstate/ssstatesig: Change timestamp clamping to hash output only
- docs: Gather dependencies in poky.yaml.in



- docs: standards.md: add a section on admonitions
- gstreamer1.0: improve test reliability
- linux-yocto/5.10: update to v5.10.227
- linux-yocto/5.15: update to v5.15.175
- llvm: reduce size of -dbg package
- lttnng-modules: fix build error after kernel update to 5.15.171
- migration-guides: add release notes for 4.0.23
- ninja: fix build with python 3.13
- oeqa/utis/gitarchive: Return tag name and improve exclude handling
- ovmf-native: remove .pyc files from install
- package.bbclass: Use shlex instead of deprecated pipes
- package\_rpm: restrict rpm to 4 threads
- package\_rpm: use zstd's default compression level
- poky.conf: add new tested distros
- poky.conf: bump version for 4.0.24
- poky.yaml.in: add missing locales dependency
- python3: upgrade to 3.10.16
- ref-manual: SSTATE\_MIRRORS/SOURCE\_MIRROR\_URL: add instructions for mirror authentication
- ref-manual: classes: fix bin\_package description
- ref-manual: devtool-reference: add warning note on deploy-target and shared objects
- ref-manual: move runtime-testing section to the test-manual
- ref-manual: packages: move ptest section to the test-manual
- ref-manual: system-requirements: update list of supported distros
- ref-manual: use standardized method accross both ubuntu and debian for locale install
- resulttool: Add --logfile-archive option to store mode
- resulttool: Allow store to filter to specific revisions
- resulttool: Clean up reproducible build logs
- resulttool: Fix passthrough of --all files in store mode
- resulttool: Handle ltp rawlogs as well as ptest
- resulttool: Improve repo layout for oeselftest results
- resulttool: Trim the precision of duration information
- resulttool: Use single space indentation in json output

- rootfs-postcommands.bbclass: make opkg status reproducible
- rxvt-unicode.inc: disable the terminfo installation by setting TIC to :
- sanity: check for working user namespaces
- scripts/install-buildtools: Update to 4.0.22
- selftest/reproducible: Clean up pathnames
- selftest/reproducible: Drop rawlogs
- test-manual: reproducible-builds.rst: document *OEQA\_REPRODUCIBLE\_TEST\_TARGET* and *OEQA\_REPRODUCIBLE\_TEST\_SSTATE\_TARGETS*
- test-manual: reproducible-builds.rst: show how to build a single package
- toolchain-shar-extract.sh: exit when post-relocate-setup.sh fails
- tzdata & tzcode-native: upgrade 2024b
- udev-extraconf: fix network.sh script did not configure hotplugged interfaces
- unzip: Fix configure tests to use modern C
- webkitgtk: Fix build on 32bit arm
- webkitgtk: fix perl-native dependency
- webkitgtk: reduce size of -dbg package
- wireless-regdb: upgrade to 2024.10.07

### Known Issues in Yocto-4.0.24

- N/A

### Contributors to Yocto-4.0.24

Thanks to the following people who contributed to this release:

- Aleksandar Nikolic
- Alex Kiernan
- Alexander Kanavin
- Alexandre Belloni
- Antonin Godard
- Archana Polampalli
- Bruce Ashfield
- Changqing Li
- Chen Qi
- Chris Laplante
- Divya Chellam

- Ernst Persson
- Guénaél Muller
- Hitendra Prajapati
- Hongxu Jia
- Jiaying Song
- Jinfeng Wang
- Khem Raj
- Lee Chee Yang
- Liyin Zhang
- Louis Rannou
- Markus Volk
- Mikko Rapeli
- Ovidiu Panait
- Peter Kjellerstedt
- Peter Marko
- Regis Dargent
- Richard Purdie
- Rohini Sangam
- Ross Burton
- Soumya Sambu
- Steve Sakoman
- Trevor Gamblin
- Vijay Anusuri
- Wang Mingyu
- Yogita Urade
- Zahir Hussain

## Repositories / Downloads for Yocto-4.0.24

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.24](#)
- Git Revision: [f50532593651dff82bc952288d786c55038c2c86](#)

- Release Artefact: poky-f50532593651dff82bc952288d786c55038c2c86
- sha: 0aa062d19510394748db9a2d6ded2d764f435383296d9c94fb6b25755280556e
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.24/poky-f50532593651dff82bc952288d786c55038c2c86.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.24/poky-f50532593651dff82bc952288d786c55038c2c86.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: kirkstone
- Tag: yocto-4.0.24
- Git Revision: a270d4c957259761bcc7382fcc54642a02f9fc7d
- Release Artefact: oecore-a270d4c957259761bcc7382fcc54642a02f9fc7d
- sha: b08b9b16c8ffa587d521ad28e24e38c79d757a6f0839d18165ebac3081a34b68
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.24/oecore-a270d4c957259761bcc7382fcc54642a02f9fc7d.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.24/oecore-a270d4c957259761bcc7382fcc54642a02f9fc7d.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.24
- Git Revision: 87c22abb1f11be430caf4372e6b833dc7d77564e
- Release Artefact: meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e
- sha: f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.24/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.24/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.24
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.24/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.24/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

**bitbake**

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.24
- Git Revision: 3f88b005244a0afb5d5c7260e54a94a453ec9b3e
- Release Artefact: bitbake-3f88b005244a0afb5d5c7260e54a94a453ec9b3e
- sha: 31f442b72ec7d81ca75509b1a7179c3fe3942528b1e31c823b21a413244bd15b
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.24/bitbake-3f88b005244a0afb5d5c7260e54a94a453ec9b3e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.24/bitbake-3f88b005244a0afb5d5c7260e54a94a453ec9b3e.tar.bz2>

**yocto-docs**

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.24
- Git Revision: 3128bf149f40928e6c2a3e264590a0c6c9778c6a

## 17.11.27 Release notes for Yocto-4.0.25 (Kirkstone)

### Security Fixes in Yocto-4.0.25

- avahi: Fix CVE-2024-52616
- binutils: Fix CVE-2024-53589
- gdb: Fix CVE-2024-53589
- go: Fix CVE-2024-34155, CVE-2024-34156, CVE-2024-34158 and CVE-2024-45336
- gstreamer1.0: Ignore CVE-2024-47537, CVE-2024-47539, CVE-2024-47540, CVE-2024-47543, CVE-2024-47544, CVE-2024-47545, CVE-2024-47538, CVE-2024-47541, CVE-2024-47542, CVE-2024-47600, CVE-2024-47607, CVE-2024-47615, CVE-2024-47835, CVE-2024-47546, CVE-2024-47596, CVE-2024-47597, CVE-2024-47598, CVE-2024-47599, CVE-2024-47601, CVE-2024-47777, CVE-2024-47778, CVE-2024-47834, CVE-2024-47602, CVE-2024-47603, CVE-2024-47613, CVE-2024-47774, CVE-2024-47775 and CVE-2024-47776
- linux-yocto/5.15: Fix CVE-2024-36476, CVE-2024-55916, CVE-2024-56369, CVE-2024-56626, CVE-2024-56627, CVE-2024-56715, CVE-2024-56716, CVE-2024-57802, CVE-2024-57807, CVE-2024-57841, CVE-2024-57890, CVE-2024-57896, CVE-2024-57900, CVE-2024-57910, CVE-2024-57911, CVE-2024-57938, CVE-2024-57951, CVE-2025-21631, CVE-2025-21665, CVE-2025-21666, CVE-2025-21669, CVE-2025-21680, CVE-2025-21683, CVE-2025-21694, CVE-2025-21697 and CVE-2025-21699
- ofono: Fix CVE-2024-7539, CVE-2024-7540, CVE-2024-7541, CVE-2024-7542, CVE-2024-7543, CVE-2024-7544, CVE-2024-7545, CVE-2024-7546 and CVE-2024-7547
- openssl: Fix CVE-2024-13176

- rsync: Fix [CVE-2024-12084](#), [CVE-2024-12085](#), [CVE-2024-12086](#), [CVE-2024-12087](#), [CVE-2024-12088](#) and [CVE-2024-12747](#)
- ruby: Fix [CVE-2024-49761](#)
- socat: Fix [CVE-2024-54661](#)
- vte: Fix [CVE-2024-37535](#)
- wget: Fix [CVE-2024-10524](#)

### Fixes in Yocto-4.0.25

- bitbake: tests/fetch: Fix git shallow test failure with git >= 2.48
- build-appliance-image: Update to kirkstone head revision
- classes-global/insane: Look up all runtime providers for file-rdeps
- classes/nativesdk: also override *TUNE\_PKGARCH*
- classes/qemu: use tune to select QEMU\_EXTRAOPTIONS, not package architecture
- cmake: apply parallel build settings to ptest tasks
- dev-manual/building: document the initramfs-framework recipe
- docs: Update autobuilder URLs to valkyrie
- documentation: Fix typo in standards.md
- glibc: Suppress GCC -Os warning on user2netname for sunrpc
- glibc: stable 2.35 branch updates
- lib/packagedata.py: Add API to iterate over rprovides
- linux-yocto/5.15: upgrade to v5.15.178
- migration-guides: add release notes for 4.0.24
- openssl: upgrade to 3.0.16
- poky.conf: bump version for 4.0.25
- python3: Treat UID/GID overflow as failure
- rsync: Delete pedantic errors re-ordering patch
- rsync: upgrade to 3.2.7
- rust-common.bbclass: soft assignment for RUSTLIB path
- scripts/install-buildtools: Update to 4.0.23
- test-manual/reproducible-builds: fix reproducible links

### Known Issues in Yocto-4.0.25

- N/A

### Contributors to Yocto-4.0.25

- Aleksandar Nikolic
- Alexander Kanavin
- Antonin Godard
- Archana Polampalli
- Bruce Ashfield
- Deepesh Varatharajan
- Divya Chellam
- Joshua Watt
- Khem Raj
- Lee Chee Yang
- Nikhil R
- Pedro Ferreira
- Peter Marko
- Praveen Kumar
- Richard Purdie
- Ross Burton
- Simon A. Eugster
- Steve Sakoman
- Yash Shinde
- Yogita Urade
- Zhang Peng

### Repositories / Downloads for Yocto-4.0.25

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.25](#)
- Git Revision: [b5aa03f336c121269551f9e7baed4c677c76bb39](#)
- Release Artefact: [poky-b5aa03f336c121269551f9e7baed4c677c76bb39](#)
- sha: [7afbcb25f0dd89a4fb6dd4c5945061705ef9ce79a6863806278603273c2b3b4a](#)

- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.25/poky-b5aa03f336c121269551f9e7baed4c677c76bb39.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.25/poky-b5aa03f336c121269551f9e7baed4c677c76bb39.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: kirkstone
- Tag: yocto-4.0.25
- Git Revision: 5a794fd244f7fdeb426bd5e3def6b4effc0e8c62
- Release Artefact: oecore-5a794fd244f7fdeb426bd5e3def6b4effc0e8c62
- sha: 8fc93109693e5f4702b3fe0633b6be833605291b3d595dc8bdeb6379f40cd2de
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.25/oecore-5a794fd244f7fdeb426bd5e3def6b4effc0e8c62.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.25/oecore-5a794fd244f7fdeb426bd5e3def6b4effc0e8c62.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.25
- Git Revision: 87c22abb1f11be430caf4372e6b833dc7d77564e
- Release Artefact: meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e
- sha: f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.25/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.25/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.25
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.25/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.25/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>



- Branch: 2.0
- Tag: yocto-4.0.25
- Git Revision: e71f1ce53cf3b8320caa481ae62d1ce2900c4670
- Release Artefact: bitbake-e71f1ce53cf3b8320caa481ae62d1ce2900c4670
- sha: 007eef35174586c85b233f4ec91578956fe21e0236f7ca2c3f90f9d034f94b5b
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.25/bitbake-e71f1ce53cf3b8320caa481ae62d1ce2900c4670.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.25/bitbake-e71f1ce53cf3b8320caa481ae62d1ce2900c4670.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.25
- Git Revision: c6dce0c77481dee7b0a0fcdc803f755cececef234

## 17.11.28 Release notes for Yocto-4.0.26 (Kirkstone)

### Security Fixes in Yocto-4.0.26

- bind: Fix CVE-2024-11187 and CVE-2024-12705
- binutils: Fix CVE-2025-0840
- elfutils: Fix CVE-2025-1352 and CVE-2025-1372
- ffmpeg: Fix CVE-2024-28661, CVE-2024-35369, CVE-2024-36613, CVE-2024-36616, CVE-2024-36617, CVE-2024-36618, CVE-2025-0518 and CVE-2025-25473
- ffmpeg: Ignore CVE-2023-46407, CVE-2023-47470, CVE-2024-7272, CVE-2024-22860, CVE-2024-22861 and CVE-2024-22862
- freetype: Fix CVE-2025-27363
- gnutls: Fix CVE-2024-12243
- grub: Fix CVE-2024-45774, CVE-2024-45775, CVE-2024-45776, CVE-2024-45777, CVE-2024-45778, CVE-2024-45779, CVE-2024-45780, CVE-2024-45781, CVE-2024-45782, CVE-2024-45783, CVE-2024-56737, CVE-2025-0622, CVE-2025-0624, CVE-2025-0677, CVE-2025-0684, CVE-2025-0685, CVE-2025-0686, CVE-2025-0689, CVE-2025-0678, CVE-2025-0690, CVE-2025-1118 and CVE-2025-1125
- gstreamer1.0-rtsp-server: fix CVE-2024-44331
- libarchive: Fix CVE-2025-25724
- libarchive: Ignore CVE-2025-1632
- libcap: Fix CVE-2025-1390

- **linux-yocto/5.10:** Fix CVE-2024-36476, CVE-2024-43098, CVE-2024-47143, CVE-2024-48881, CVE-2024-50051, CVE-2024-50074, CVE-2024-50082, CVE-2024-50083, CVE-2024-50099, CVE-2024-50115, CVE-2024-50116, CVE-2024-50117, CVE-2024-50142, CVE-2024-50148, CVE-2024-50150, CVE-2024-50151, CVE-2024-50167, CVE-2024-50168, CVE-2024-50171, CVE-2024-50185, CVE-2024-50192, CVE-2024-50193, CVE-2024-50194, CVE-2024-50195, CVE-2024-50198, CVE-2024-50201, CVE-2024-50202, CVE-2024-50205, CVE-2024-50208, CVE-2024-50209, CVE-2024-50229, CVE-2024-50230, CVE-2024-50233, CVE-2024-50234, CVE-2024-50236, CVE-2024-50237, CVE-2024-50251, CVE-2024-50262, CVE-2024-50264, CVE-2024-50265, CVE-2024-50267, CVE-2024-50268, CVE-2024-50269, CVE-2024-50273, CVE-2024-50278, CVE-2024-50279, CVE-2024-50282, CVE-2024-50287, CVE-2024-50292, CVE-2024-50296, CVE-2024-50299, CVE-2024-50301, CVE-2024-50302, CVE-2024-53042, CVE-2024-53052, CVE-2024-53057, CVE-2024-53059, CVE-2024-53060, CVE-2024-53061, CVE-2024-53063, CVE-2024-53066, CVE-2024-53096, CVE-2024-53097, CVE-2024-53101, CVE-2024-53103, CVE-2024-53104, CVE-2024-53145, CVE-2024-53146, CVE-2024-53150, CVE-2024-53155, CVE-2024-53156, CVE-2024-53157, CVE-2024-53161, CVE-2024-53165, CVE-2024-53171, CVE-2024-53173, CVE-2024-53174, CVE-2024-53194, CVE-2024-53197, CVE-2024-53217, CVE-2024-53226, CVE-2024-53227, CVE-2024-53237, CVE-2024-53239, CVE-2024-55916, CVE-2024-56548, CVE-2024-56558, CVE-2024-56567, CVE-2024-56568, CVE-2024-56569, CVE-2024-56572, CVE-2024-56574, CVE-2024-56581, CVE-2024-56587, CVE-2024-56593, CVE-2024-56595, CVE-2024-56596, CVE-2024-56598, CVE-2024-56600, CVE-2024-56601, CVE-2024-56602, CVE-2024-56603, CVE-2024-56605, CVE-2024-56606, CVE-2024-56615, CVE-2024-56619, CVE-2024-56623, CVE-2024-56629, CVE-2024-56634, CVE-2024-56642, CVE-2024-56643, CVE-2024-56648, CVE-2024-56650, CVE-2024-56659, CVE-2024-56662, CVE-2024-56670, CVE-2024-56688, CVE-2024-56698, CVE-2024-56704, CVE-2024-56716, CVE-2024-56720, CVE-2024-56723, CVE-2024-56724, CVE-2024-56728, CVE-2024-56739, CVE-2024-56746, CVE-2024-56747, CVE-2024-56748, CVE-2024-56754, CVE-2024-56756, CVE-2024-56770, CVE-2024-56779, CVE-2024-56780, CVE-2024-56781, CVE-2024-56785, CVE-2024-57802, CVE-2024-57807, CVE-2024-57850, CVE-2024-57874, CVE-2024-57890, CVE-2024-57896, CVE-2024-57900, CVE-2024-57901, CVE-2024-57902, CVE-2024-57910, CVE-2024-57911, CVE-2024-57913, CVE-2024-57922, CVE-2024-57938, CVE-2024-57939, CVE-2024-57946, CVE-2024-57951, CVE-2025-21638, CVE-2025-21687, CVE-2025-21689, CVE-2025-21692, CVE-2025-21694, CVE-2025-21697 and CVE-2025-21699
- **linux-yocto/5.15:** Fix CVE-2024-57979, CVE-2024-58034, CVE-2024-58052, CVE-2024-58055, CVE-2024-58058, CVE-2024-58063, CVE-2024-58069, CVE-2024-58071, CVE-2024-58076, CVE-2024-58083, CVE-2025-21700, CVE-2025-21703, CVE-2025-21715, CVE-2025-21722, CVE-2025-21727, CVE-2025-21731, CVE-2025-21753, CVE-2025-21756, CVE-2025-21760, CVE-2025-21761, CVE-2025-21762, CVE-2025-21763, CVE-2025-21764, CVE-2025-21796, CVE-2025-21811, CVE-2025-21887, CVE-2025-21898, CVE-2025-21904, CVE-2025-21905, CVE-2025-21912, CVE-2025-21917, CVE-2025-21919, CVE-2025-21920, CVE-2025-21922, CVE-2025-21934, CVE-2025-21943, CVE-2025-21948 and CVE-2025-21951
- **libpcrc2:** Ignore CVE-2022-1586
- **libtasn1:** Fix CVE-2024-12133
- **libxml2:** Fix CVE-2022-49043, CVE-2024-56171, CVE-2025-24928 and CVE-2025-27113
- **libxslt:** Fix CVE-2024-55549 and CVE-2025-24855

- llvm: Fix [CVE-2024-0151](#)
- mpg123: Fix [CVE-2024-10573](#)
- openssh: Fix [CVE-2025-26465](#)
- ovmf: Revert Fix for [CVE-2023-45236](#) [CVE-2023-45237](#)
- perl: Ignore [CVE-2023-47038](#)
- puzzles: Ignore [CVE-2024-13769](#), [CVE-2024-13770](#) and [CVE-2025-0837](#)
- python3: Fix [CVE-2025-0938](#)
- ruby: Fix [CVE-2024-41946](#), [CVE-2025-27219](#) and [CVE-2025-27220](#)
- subversion: Ignore [CVE-2024-45720](#)
- systemd: Fix [CVE-2022-3821](#), [CVE-2022-4415](#), [CVE-2022-45873](#) and [CVE-2023-7008](#)
- tiff: mark [CVE-2023-30774](#) as patched with existing patch
- u-boot: Fix [CVE-2022-2347](#), [CVE-2022-30767](#), [CVE-2022-30790](#), [CVE-2024-57254](#), [CVE-2024-57255](#), [CVE-2024-57256](#), [CVE-2024-57257](#), [CVE-2024-57258](#) and [CVE-2024-57259](#)
- vim: Fix [CVE-2025-1215](#), [CVE-2025-22134](#), [CVE-2025-24014](#), [CVE-2025-26603](#), [CVE-2025-27423](#) and [CVE-2025-29768](#)
- xserver-xorg: Fix [CVE-2022-49737](#), [CVE-2025-26594](#), [CVE-2025-26595](#), [CVE-2025-26596](#), [CVE-2025-26597](#), [CVE-2025-26598](#), [CVE-2025-26599](#), [CVE-2025-26600](#) and [CVE-2025-26601](#)
- xwayland: Fix [CVE-2022-49737](#), [CVE-2024-9632](#), [CVE-2024-21885](#), [CVE-2024-21886](#), [CVE-2024-31080](#), [CVE-2024-31081](#), [CVE-2024-31083](#), [CVE-2025-26594](#), [CVE-2025-26595](#), [CVE-2025-26596](#), [CVE-2025-26597](#), [CVE-2025-26598](#), [CVE-2025-26599](#), [CVE-2025-26600](#) and [CVE-2025-26601](#)
- zlib: Fix [CVE-2014-9485](#)

### Fixes in Yocto-4.0.26

- bind: Upgrade to 9.18.33
- bitbake: cache: bump cache version
- bitbake: siggen.py: Improve taskhash reproducibility
- boost: fix do\_fetch error
- build-appliance-image: Update to kirkstone head revision
- contributor-guide/submit-changes: add policy on AI generated code
- cve-update-nvd2-native: handle missing vulnStatus
- docs: Add favicon for the documentation html
- docs: Remove all mention of core-image-lsb
- libtasn1: upgrade to 4.20.0
- libxcrypt-compat: Remove libcrypt.so to fix conflict with libcrypt

- libxml2: fix compilation of explicit child axis in pattern
- linux-yocto/5.10: update to v5.10.234
- linux-yocto/5.15: update to v5.15.179
- mesa: Fix missing GLES3 headers in SDK sysroot
- mesa: Update *SRC\_URI*
- meta: Enable '-o pipefail' for the SDK installer
- migration-guides: add release notes for 4.0.25
- poky.conf: add ubuntu2404 to *SANITY\_TESTED\_DISTROS*
- poky.conf: bump version for 4.0.26
- procps: replaced one use of fputs(3) with a write(2) call
- ref-manual: don't refer to poky-lsb
- scripts/install-buildtools: Update to 4.0.24
- scritps/runqemu: Ensure we only have two serial ports
- systemd: upgrade to 250.14
- tzcode-native: Fix compiler setting from 2023d version
- tzcode: Update *SRC\_URI*
- tzdata/tzcode-native: upgrade 2025a
- vim: Upgrade to 9.1.1198
- virglrenderer: fix do\_fetch error
- vulnerabilities/classes: remove references to cve-check text format
- xz: Update *SRC\_URI*
- yocto-uninative: Update to 4.7 for glibc 2.41

### Known Issues in Yocto-4.0.26

- N/A

### Contributors to Yocto-4.0.26

Thanks to the following people who contributed to this release:

- Aleksandar Nikolic
- Alessio Cascone
- Antonin Godard
- Archana Polampalli
- Ashish Sharma
- Bruce Ashfield

- Carlos Dominguez
- Deepesh Varatharajan
- Divya Chellam
- Guocai He
- Hitendra Prajapati
- Hongxu Jia
- Jiaying Song
- Johannes Kauffmann
- Kai Kang
- Lee Chee Yang
- Libo Chen
- Marta Rybczynska
- Michael Halstead
- Mingli Yu
- Moritz Haase
- Narpat Mali
- Paulo Neves
- Peter Marko
- Priyal Doshi
- Richard Purdie
- Robert Yang
- Ross Burton
- Sakib Sajal
- Steve Sakoman
- Vijay Anusuri
- Yogita Urade
- Zhang Peng

## Repositories / Downloads for Yocto-4.0.26

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.26](#)

- Git Revision: [d70d287a77d5026b698ac237ab865b2dafd36bb8](#)
- Release Artefact: [poky-d70d287a77d5026b698ac237ab865b2dafd36bb8](#)
- sha: [3ebfadb8bff4c1ca12b3cf3e4ef6e3ac2ce52b73570266daa98436c9959249f2](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.26/poky-d70d287a77d5026b698ac237ab865b2dafd36bb8.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.26/poky-d70d287a77d5026b698ac237ab865b2dafd36bb8.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.26](#)
- Git Revision: [1efbe1004bc82e7c14c1e8bd4ce644f5015c3346](#)
- Release Artefact: [oecore-1efbe1004bc82e7c14c1e8bd4ce644f5015c3346](#)
- sha: [d3805e034dabd0865dbf55488b2c16d4ea0351d37aa826f0054a6bfdde5a8be9](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.26/oecore-1efbe1004bc82e7c14c1e8bd4ce644f5015c3346.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.26/oecore-1efbe1004bc82e7c14c1e8bd4ce644f5015c3346.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.26](#)
- Git Revision: [87c22abb1f11be430caf4372e6b833dc7d77564e](#)
- Release Artefact: [meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e](#)
- sha: [f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.26/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.26/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.26](#)
- Git Revision: [d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- Release Artefact: [meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- sha: [c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d](#)

- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.26/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.26/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.26
- Git Revision: 046871d9fd76efdca7b72718b328d8f545523f7e
- Release Artefact: bitbake-046871d9fd76efdca7b72718b328d8f545523f7e
- sha: e9df0a9f5921b583b539188d66b23f120e1751000e7822e76c3391d5c76ee21a
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.26/bitbake-046871d9fd76efdca7b72718b328d8f545523f7e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.26/bitbake-046871d9fd76efdca7b72718b328d8f545523f7e.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.26
- Git Revision: 9b4c36f7b02dd4bedfec90206744a1e90e37733c

## 17.11.29 Release notes for Yocto-4.0.27 (Kirkstone)

### Security Fixes in Yocto-4.0.27

- binutils: Fix CVE-2025-1178
- busybox: fix CVE-2023-39810
- connman :fix CVE-2025-32743
- curl: Ignore CVE-2025-0725
- ghostscript: Fix CVE-2025-27830, CVE-2025-27831, CVE-2025-27832, CVE-2025-27834, CVE-2025-27835 and CVE-2025-27836
- ghostscript: Ignore CVE-2024-29507, CVE-2025-27833 and CVE-2025-27837
- glib-2.0: Fix CVE-2025-3360
- go: Fix CVE-2025-22871
- libarchive: Ignore CVE-2024-48615
- libpam: Fix CVE-2024-10041
- libsoup-2.4: Fix CVE-2024-52532, CVE-2025-32906 and CVE-2025-32909

- libsoup: Fix CVE-2024-52532, CVE-2025-32906, CVE-2025-32909, CVE-2025-32910, CVE-2025-32911, CVE-2025-32912, CVE-2025-32913 and CVE-2025-32914
- libxml2: Fix CVE-2025-32414 and CVE-2025-32415
- ofono: Fix CVE-2024-7537
- perl: Fix CVE-2024-56406
- ppp: Fix CVE-2024-58250
- python3-setuptools: Fix CVE-2024-6345
- qemu: Ignore CVE-2023-1386
- ruby: Fix CVE-2024-43398
- sqlite3: Fix CVE-2025-29088
- systemd: Ignore CVE-2022-3821, CVE-2022-4415 and CVE-2022-45873

### Fixes in Yocto-4.0.27

- Revert "cve-update-nvd2-native: Tweak to work better with NFS DL\_DIR"
- build-appliance-image: Update to kirkstone head revision
- cve-update-nvd2-native: add workaround for json5 style list
- docs: Fix dead links that use the *DISTRO* macro
- docs: manuals: remove repeated word
- docs: poky.yaml: introduce DISTRO\_LATEST\_TAG
- glibc: Add single-threaded fast path to rand()
- glibc: stable 2.35 branch updates
- module.bbclass: add KBUILD\_EXTRA\_SYMBOLS to install
- perl: enable \_GNU\_SOURCE define via d\_gnulibc
- poky.conf: bump version for 4.0.27
- ref-manual/variables.rst: document autotools class related variables
- scripts/install-buildtools: Update to 4.0.26
- systemd: backport patch to fix journal issue
- systemd: systemd-journald fails to setup LogNamespace
- tzdata/tzcode-native: upgrade to 2025b

### Known Issues in Yocto-4.0.27

- N/A



## Contributors to Yocto-4.0.27

- Aleksandar Nikolic
- Alexander Kanavin
- Alon Bar-Lev
- Andrew Kreimer
- Antonin Godard
- Chen Qi
- Deepesh Varatharajan
- Divya Chellam
- Haitao Liu
- Haixiao Yan
- Hitendra Prajapati
- Peter Marko
- Praveen Kumar
- Priyal Doshi
- Shubham Kulkarni
- Soumya Sambu
- Steve Sakoman
- Vijay Anusuri
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.27

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.27](#)
- Git Revision: [ab9a994a8cd8e06b519a693db444030999d273b7](#)
- Release Artefact: [poky-ab9a994a8cd8e06b519a693db444030999d273b7](#)
- sha: [77a366c17cf29eef15c6ff3f44e73f81c07288c723fd4a6dbd8c7ee9b79933f3](#)
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.27/poky-ab9a994a8cd8e06b519a693db444030999d273b7.tar.bz2>                      <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.27/poky-ab9a994a8cd8e06b519a693db444030999d273b7.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>

- Branch: `kirkstone`
- Tag: `yocto-4.0.27`
- Git Revision: `e8be08a624b2d024715a5c8b0c37f2345a02336b`
- Release Artefact: `oecore-e8be08a624b2d024715a5c8b0c37f2345a02336b`
- sha: `cc5b0fadab021c6dc61f37fc4ff01a1cf657e7c219488ce264bede42f7f6212f`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.27/oecore-e8be08a624b2d024715a5c8b0c37f2345a02336b.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.27/oecore-e8be08a624b2d024715a5c8b0c37f2345a02336b.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.27`
- Git Revision: `87c22abb1f11be430caf4372e6b833dc7d77564e`
- Release Artefact: `meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e`
- sha: `f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.27/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.27/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.27`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.27/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.27/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.27`
- Git Revision: `046871d9fd76efdca7b72718b328d8f545523f7e`
- Release Artefact: `bitbake-046871d9fd76efdca7b72718b328d8f545523f7e`

- sha: e9df0a9f5921b583b539188d66b23f120e1751000e7822e76c3391d5c76ee21a
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.27/bitbake-046871d9fd76efdca7b72718b328d8f545523f7e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.27/bitbake-046871d9fd76efdca7b72718b328d8f545523f7e.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: kirkstone
- Tag: yocto-4.0.27
- Git Revision: 0d51e553d5f83eea6634e03ddc9c7740bf72fcea

### 17.11.30 Release notes for Yocto-4.0.28 (Kirkstone)

#### Security Fixes in Yocto-4.0.28

- binutils: Fix CVE-2025-1180, CVE-2025-1182, CVE-2025-5244 and CVE-2025-5245
- connman: Fix CVE-2025-32366
- ffmpeg: Fix CVE-2025-1373, CVE-2025-22919 and CVE-2025-22921
- ffmpeg: Ignore CVE-2022-48434
- ghostscript: Fix CVE-2025-48708
- git: Fix CVE-2024-50349 and CVE-2024-52006
- glib-2.0: Fix CVE-2025-4373
- glibc: Fix for CVE-2025-4802
- go: Fix CVE-2025-4673
- go: ignore CVE-2024-3566
- icu: Fix CVE-2025-5222
- iputils: Fix CVE-2025-47268
- libsoup-2.4: Fix CVE-2025-2784, CVE-2025-4476, CVE-2025-4948, CVE-2025-4969, CVE-2025-32050, CVE-2025-32052, CVE-2025-32053, CVE-2025-32907, CVE-2025-32910, CVE-2025-32911, CVE-2025-32912, CVE-2025-32913, CVE-2025-32914, CVE-2025-46420 and CVE-2025-46421
- libsoup: Fix CVE-2025-2784, CVE-2025-4476, CVE-2025-4948, CVE-2025-4969, CVE-2025-32050, CVE-2025-32051, CVE-2025-32052, CVE-2025-32053, CVE-2025-32907, CVE-2025-46420 and CVE-2025-46421
- linux-yocto/5.15: Fix CVE-2024-26952, CVE-2025-21941, CVE-2025-21957, CVE-2025-21959, CVE-2025-21962, CVE-2025-21963, CVE-2025-21964, CVE-2025-21968, CVE-2025-21996, CVE-2025-22018, CVE-2025-22020, CVE-2025-22035, CVE-2025-22054, CVE-2025-22056, CVE-2025-22063, CVE-2025-22066, CVE-2025-22081, CVE-2025-22097, CVE-2025-23136, CVE-2025-37785, CVE-2025-37803, CVE-2025-37805, CVE-2025-38152, CVE-2025-39728 and CVE-2025-39735
- net-tools: Fix CVE-2025-46836

- openssh: Fix [CVE-2025-32728](#)
- python3: Fix [CVE-2024-12718](#), [CVE-2025-0938](#), [CVE-2025-4138](#), [CVE-2025-4330](#), [CVE-2025-4435](#), [CVE-2025-4516](#) and [CVE-2025-4517](#)
- python3-requests: Fix [CVE-2024-47081](#)
- python3-setuptools: Fix [CVE-2025-47273](#)
- ruby: Fix [CVE-2025-27221](#)
- screen: Fix [CVE-2025-46802](#), [CVE-2025-46804](#) and [CVE-2025-46805](#)
- taglib: Fix [CVE-2023-47466](#)

### Fixes in Yocto-4.0.28

- babeltrace/libatomic-ops: correct the [SRC\\_URI](#)
- brief-yoctoprojectqs/ref-manual: Switch to new CDN
- bsp guide: update kernel version example to 6.12
- bsp-guide: update lonely "4.12" kernel reference to "6.12"
- build-appliance-image: Update to kirkstone head revision
- cmake: Correctly handle cost data of tests with arbitrary chars in name
- conf.py: tweak SearchEnglish to be hyphen-friendly
- contributor-guide/submit-changes: encourage patch version changelogs
- dev-manual/sbom.rst: fix wrong build outputs
- docs: Clean up explanation of minimum required version numbers
- docs: README: specify how to contribute instead of pointing at another file
- docs: conf.py: silence SyntaxWarning on js\_splitter\_code
- e2fsprogs: removed 'sed -u' option
- ffmpeg: Add "libswresample libavcodec" to [CVE\\_PRODUCT](#)
- ffmpeg: upgrade to 5.0.3
- gcc: AArch64 - Fix strict-align cpymem/setmem
- glibc: nptl Fix indentation
- glibc: nptl Remove unnecessary catch-all-wake in condvar group switch
- glibc: nptl Remove unnecessary quadruple check in pthread\_cond\_wait
- glibc: nptl Update comments and indentation for new condvar implementation
- glibc: nptl Use a single loop in pthread\_cond\_wait instead of a nested loop
- glibc: nptl Use all of g1\_start and g\_signals
- glibc: nptl rename \_\_condvar\_quiesce\_and\_switch\_g1

- glibc: pthreads NPTL lost wakeup fix 2
- kernel.bbclass: add original package name to *RPROVIDES* for -image and -base
- libpng: Improve ptest
- linux-yocto/5.15: update to v5.15.184
- migration-guides: add release notes for 4.0.26 and 4.0.27
- nfs-utils: don't use signals to shut down nfs server.
- poky.conf: bump version for 4.0.28
- python3: upgrade to 3.10.18
- ref-manual/release-process: update releases.svg
- ref-manual/variables.rst: document *INHIBIT\_DEFAULT\_RUST\_DEPS* *INHIBIT\_UPDATERCD\_BBCLASS* *SSTATE\_SKIP\_CREATION* *WIC\_CREATE\_EXTRA\_ARGS* *IMAGE\_ROOTFS\_MAXSIZE* *INTRAMFS\_MAXSIZE*
- ref-manual: clarify *KCONFIG\_MODE* default behaviour
- ref-manual: classes: nativesdk: move note to appropriate section
- ref-manual: classes: reword to clarify that native/nativesdk options are exclusive
- ref-manual: kernel-fitimage.bbclass does not use *SPL\_SIGN\_KEYNAME*
- scripts/install-buildtools: Update to 4.0.27
- sphinx-lint: role missing opening tag colon
- sphinx-lint: trailing whitespace
- sphinx-lint: unbalanced inline literal markup
- sysstat: correct the *SRC\_URI*
- systemtap: add sysroot Python paths to configure flags
- test-manual/intro: remove Buildbot version used
- util-linux: Add fix to isolate test fstab entries using CUSTOM\_FSTAB
- xz: Update *LICENSE* variable for xz packages

### Known Issues in Yocto-4.0.28

- N/A

### Contributors to Yocto-4.0.28

- Aditya Tayade
- Adrian Freihofer
- Aleksandar Nikolic
- Alper Ak

- Antonin Godard
- Archana Polampalli
- Ashish Sharma
- Bruce Ashfield
- Carlos Sánchez de La Lama
- Changqing Li
- Christos Gavros
- Colin Pinnell McAllister
- Deepesh Varatharajan
- Divya Chellam
- Enrico Jörns
- Etienne Cordonnier
- Guocai He
- Harish Sadineni
- Hitendra Prajapati
- Jiaying Song
- Lee Chee Yang
- Martin Jansa
- Moritz Haase
- NeilBrown
- Peter Marko
- Poonam Jadhav
- Praveen Kumar
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Soumya Sambu
- Steve Sakoman
- Sundeep KOKKONDA
- Sunil Dora
- Trevor Woerner
- Vijay Anusuri

- Virendra Thakur
- Yi Zhao
- aszh07

## Repositories / Downloads for Yocto-4.0.28

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.28`
- Git Revision: `78c9cb3eaf071932567835742608404d5ce23cc4`
- Release Artefact: `poky-78c9cb3eaf071932567835742608404d5ce23cc4`
- sha: `9c73c6f89e70c2041a52851e5cc582e5a2f05ad2fdc110d2c518f2c4994e8de3`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.28/poky-78c9cb3eaf071932567835742608404d5ce23cc4.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.28/poky-78c9cb3eaf071932567835742608404d5ce23cc4.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.28`
- Git Revision: `75e54301c5076eb0454aee33c870adf078f563fd`
- Release Artefact: `oecore-75e54301c5076eb0454aee33c870adf078f563fd`
- sha: `c5ffceab90881c4041ec4304da8b7b32d9c1f89a4c63ee7b8cbd53c796b0187b`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.28/oecore-75e54301c5076eb0454aee33c870adf078f563fd.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.28/oecore-75e54301c5076eb0454aee33c870adf078f563fd.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `kirkstone`
- Tag: `yocto-4.0.28`
- Git Revision: `87c22abb1f11be430caf4372e6b833dc7d77564e`
- Release Artefact: `meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e`
- sha: `f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.28/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.28/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.28`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.28/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.28/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.28`
- Git Revision: `046871d9fd76efdca7b72718b328d8f545523f7e`
- Release Artefact: `bitbake-046871d9fd76efdca7b72718b328d8f545523f7e`
- sha: `e9df0a9f5921b583b539188d66b23f120e1751000e7822e76c3391d5c76ee21a`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.28/bitbake-046871d9fd76efdca7b72718b328d8f545523f7e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.28/bitbake-046871d9fd76efdca7b72718b328d8f545523f7e.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `kirkstone`
- Tag: `yocto-4.0.28`
- Git Revision: `0bf3dcef1caa80fb047bf9c3514314ab658e30ea`

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.28`
- Git Revision: `97cd3ee7f3bf1de8454708d1852ea9cbbd45c39b`



### 17.11.31 Release notes for Yocto-4.0.29 (Kirkstone)

#### Security Fixes in Yocto-4.0.29

- avahi: Fix CVE-2024-52615
- binutils: Fix CVE-2025-7545 and CVE-2025-7546
- coreutils: Fix CVE-2025-5278
- curl: Fix CVE-2024-11053 and CVE-2025-0167
- dropbear: Fix CVE-2025-47203
- ffmpeg: Ignore CVE-2022-3109 and CVE-2022-3341
- gdk-pixbuf: Fix CVE-2025-7345
- ghostscript: Ignore CVE-2025-46646
- gnupg: Fix CVE-2025-30258
- gnutls: Fix CVE-2025-6395, CVE-2025-32988, CVE-2025-32989 and CVE-2025-32990
- iputils: Fix CVE-2025-48964
- libarchive: Fix CVE-2025-5914, CVE-2025-5915, CVE-2025-5916 and CVE-2025-5917
- libpam: Fix CVE-2025-6020
- libsoup-2.4: Fix CVE-2025-4945
- libsoup-2.4: Fix CVE-2025-4969 (update patch)
- libsoup: Fix CVE-2025-4945, CVE-2025-6021, CVE-2025-6170, CVE-2025-49794 and CVE-2025-49796
- ncurses: Fix CVE-2025-6141
- ofono: Fix CVE-2023-4232 and CVE-2023-4235
- openssl: Fix CVE-2024-41996
- python3-urllib3: Fix CVE-2025-50181
- ruby: Fix CVE-2024-43398 (update patches)
- sqlite3: Fix CVE-2025-6965 and CVE-2025-7458
- sqlite3: Ignore CVE-2025-3277
- systemd: Fix CVE-2025-4598
- xwayland: Fix CVE-2025-49175, CVE-2025-49176, CVE-2025-49177, CVE-2025-49178, CVE-2025-49179 and CVE-2025-49180

#### Fixes in Yocto-4.0.29

- bintuils: stable 2.38 branch update
- bitbake: test/fetch: Switch u-boot based test to use our own mirror
- build-appliance-image: Update to kirkstone head revision

- conf.py: improve SearchEnglish to handle terms with dots
- db: ignore implicit-int and implicit-function-declaration issues fatal with gcc-14
- dev-manual/start.rst: added missing command in Optimize your VHDX file using DiskPart
- glibc: stable 2.35 branch updates
- gnutils: patch read buffer overrun in the "pre\_shared\_key" extension
- gnutils: patch reject zero-length version in certificate request
- linux-yocto/5.15: update to v5.15.186
- migration-guides: add release notes for 4.0.28
- oeqa/core/decorator: add decorators to skip based on *HOST\_ARCH*
- openssl: upgrade to 3.0.17
- orc: set *CVE\_PRODUCT*
- overview-manual/concepts.rst: fix sayhello hardcoded bindir
- poky.conf: bump version for 4.0.29
- python3: update CVE product
- ref-manual: document *KERNEL\_SPLIT\_MODULES* variable
- scripts/install-buildtools: Update to 4.0.28
- sudo: upgrade to 1.9.17p1
- tcf-agent: correct the *SRC\_URI*

### Known Issues in Yocto-4.0.29

- N/A

### Contributors to Yocto-4.0.29

- Aleksandar Nikolic
- Antonin Godard
- Archana Polampalli
- Bruce Ashfield
- Changqing Li
- Chen Qi
- Colin Pinnell McAllister
- Daniel Díaz
- Deepesh Varatharajan
- Divya Chellam
- Dixit Parmar

- Enrico Jörns
- Guocai He
- Hitendra Prajapati
- Lee Chee Yang
- Marco Cavallini
- Martin Jansa
- Peter Marko
- Praveen Kumar
- Richard Purdie
- Rob Woolley
- Ross Burton
- Steve Sakoman
- Vijay Anusuri
- Yash Shinde
- Yogita Urade
- Zhang Peng

## Repositories / Downloads for Yocto-4.0.29

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.29`
- Git Revision: `81ab000fa437ca04f584a3327b076f7a512dc6d0`
- Release Artefact: `poky-81ab000fa437ca04f584a3327b076f7a512dc6d0`
- sha: `2fecf3cac5c2361c201b5ae826960af92289862ec9be13837a8431138e534fd2`
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.29/poky-81ab000fa437ca04f584a3327b076f7a512dc6d0.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.29/poky-81ab000fa437ca04f584a3327b076f7a512dc6d0.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.29`
- Git Revision: `bd620eb14660075fd0f7476bbbb65d5da6293874`
- Release Artefact: `oecore-bd620eb14660075fd0f7476bbbb65d5da6293874`

- sha: f32ab195c7090268e6e87ccf8db2813cf705c517030654326d14b25d926de88e
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.29/oecore-bd620eb14660075fd0f7476bbbb65d5da6293874.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.29/oecore-bd620eb14660075fd0f7476bbbb65d5da6293874.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.29
- Git Revision: 87c22abb1f11be430caf4372e6b833dc7d77564e
- Release Artefact: meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e
- sha: f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.29/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.29/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.29
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.29/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.29/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.29
- Git Revision: 8e2d1f8de055549b2101614d85454fcd1d0f94b2
- Release Artefact: bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2
- sha: fad4e7699bae62082118e89785324b031b0af0743064caee87c91ba28549afb0
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.29/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.29/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `kirkstone`
- Tag: `yocto-4.0.29`
- Git Revision: `e916d3bad58f955b73e2c67aba975e63cd191394`

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.29`
- Git Revision: `bf855ecaf4bec4cef9bbfea2e50caa65a8339828`

### 17.11.32 Release notes for Yocto-4.0.30 (Kirkstone)

#### Security Fixes in Yocto-4.0.30

- cups: Fix CVE-2025-58060 and CVE-2025-58364
- dpkg: Fix CVE-2025-6297
- ffmpeg: Fix CVE-2023-6602, CVE-2023-6604, CVE-2023-6605, CVE-2025-1594 and CVE-2025-7700
- git: Fix CVE-2025-27613, CVE-2025-27614, CVE-2025-46334, CVE-2025-46835 and CVE-2025-48384
- glib-2.0: Fix CVE-2025-7039
- glib-2.0: Ignore CVE-2025-4056
- go: Ignore CVE-2024-24790 and CVE-2025-0913
- gstreamer1.0-plugins-base: Fix CVE-2025-47806, CVE-2025-47807 and CVE-2025-47808
- gstreamer1.0-plugins-good: Fix CVE-2025-47183 and CVE-2025-47219
- libarchive: Fix CVE-2025-5918
- libxslt: Fix CVE-2023-40403
- openssl: Fix CVE-2023-50781
- python3: Fix CVE-2025-8194
- qemu: Ignore CVE-2024-7730
- sqlite3: Revert "sqlite3: patch CVE-2025-7458"
- tiff: Fix CVE-2024-13978, CVE-2025-8176, CVE-2025-8177, CVE-2025-8534 and CVE-2025-8851
- vim: Fix CVE-2025-53905 and CVE-2025-53906
- wpa-suplicant: Fix CVE-2022-37660
- xserver-xorg: Fix CVE-2025-49175, CVE-2025-49176, CVE-2025-49177, CVE-2025-49178, CVE-2025-49179 and CVE-2025-49180

### Fixes in Yocto-4.0.30

- build-appliance-image: Update to kirkstone head revision
- default-distrovars.inc: Fix CONNECTIVITY\_CHECK\_URI redirect issue
- dev-manual/security-subjects.rst: update mailing lists
- gnupg: disable tests to avoid running target binaries at build time
- go-helloworld: fix license
- insane: Ensure that *src-uri-bad* fails correctly
- insane: Improve patch warning/error handling
- libubootenv: backport patch to fix unknown type name 'size\_t'
- llvm: fix typo in CVE-2024-0151.patch
- migration-guides: add release notes for 4.0.29
- overview-manual/yp-intro.rst: fix broken link to article
- poky.conf: bump version for 4.0.30
- pulseaudio: Add audio group explicitly
- ref-manual/classes.rst: document the testexport class
- ref-manual/system-requirements.rst: update supported distributions
- ref-manual/variables.rst: document *FIT\_CONF\_PREFIX SPL\_DTB\_BINARY* variable
- ref-manual/variables.rst: expand *IMAGE\_OVERHEAD\_FACTOR* glossary entry
- sdk: The main in the C example should return an int
- sudo: remove devtool FIXME comment
- systemd: Fix manpage build after CVE-2025-4598
- vim: not adjust script pathnames for native scripts either
- vim: upgrade to 9.1.1652

### Known Issues in Yocto-4.0.30

- N/A

### Contributors to Yocto-4.0.30

- Antonin Godard
- Archana Polampalli
- Dan McGregor
- Deepak Rathore
- Divya Chellam
- Erik Lindsten

- Guocai He
- Gyorgy Sarvari
- Hitendra Prajapati
- Jan Vermaete
- Jiaying Song
- Joao Marcos Costa
- Kyungjik Min
- Lee Chee Yang
- Mingli Yu
- Peter Marko
- Philip Lorenz
- Praveen Kumar
- Quentin Schulz
- Richard Purdie
- Steve Sakoman
- Vijay Anusuri
- Yogita Urade
- Youngseok Jeong

## Repositories / Downloads for Yocto-4.0.30

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.30](#)
- Git Revision: [51dc9c464de0703bfb6cf1ee71ac9bea20933a45](#)
- Release Artefact: [poky-51dc9c464de0703bfb6cf1ee71ac9bea20933a45](#)
- sha: [2b5db0a07598df7684975c0839e6f31515a8e78d366503feb9917ef1ca56c0b2](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.30/poky-51dc9c464de0703bfb6cf1ee71ac9bea20933a45.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.30/poky-51dc9c464de0703bfb6cf1ee71ac9bea20933a45.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.30](#)

- Git Revision: [d381eeb5e70bd0ce9e78032c909e4a23564f4dd7](#)
- Release Artefact: [oecore-d381eeb5e70bd0ce9e78032c909e4a23564f4dd7](#)
- sha: [022ab4ef5ac59ac3f01a9dacd8b1d6310cc117c6bed2e86e195ced88e0689c85](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.30/oecore-d381eeb5e70bd0ce9e78032c909e4a23564f4dd7.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.30/oecore-d381eeb5e70bd0ce9e78032c909e4a23564f4dd7.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.30](#)
- Git Revision: [87c22abb1f11be430caf4372e6b833dc7d77564e](#)
- Release Artefact: [meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e](#)
- sha: [f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.30/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.30/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.30](#)
- Git Revision: [d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- Release Artefact: [meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a](#)
- sha: [c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d](#)
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.30/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.30/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: [2.0](#)
- Tag: [yocto-4.0.30](#)
- Git Revision: [8e2d1f8de055549b2101614d85454fcd1d0f94b2](#)
- Release Artefact: [bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2](#)
- sha: [fad4e7699bae62082118e89785324b031b0af0743064caee87c91ba28549afb0](#)



- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.30/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2> <https://mirrors.kernel.org/yocto/yocto/yocto-4.0.30/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `kirkstone`
- Tag: `yocto-4.0.30`
- Git Revision: `edf7950e4d81dd31f29a58acdd8022dabd2be494`

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.30`
- Git Revision: `71a3933c609ce73ff07e5be48d9e7b03f22ef8d7`

### 17.11.33 Release notes for Yocto-4.0.31 (Kirkstone)

#### Security Fixes in Yocto-4.0.31

- binutils: Fix CVE-2025-8225, CVE-2025-11081, CVE-2025-11082 and CVE-2025-11083
- busybox: Fix CVE-2025-46394
- cmake: Fix CVE-2025-9301
- curl: Fix CVE-2025-9086
- ffmpeg: Ignore CVE-2023-6603
- ffmpeg: mark CVE-2023-6601 as Fixed
- ghostscript: Fix CVE-2025-59798, CVE-2025-59799 and CVE-2025-59800
- git: Fix CVE-2025-48386
- glib-networking: Fix CVE-2025-60018 and CVE-2025-60019
- go: Fix CVE-2025-47906 and CVE-2025-47907
- grub2: Fix CVE-2024-56738
- grub: Ignore CVE-2024-2312
- gstreamer1.0-plugins-bad: Fix CVE-2025-3887
- gstreamer1.0: Ignore CVE-2025-2759, CVE-2025-3887, CVE-2025-47183, CVE-2025-47219, CVE-2025-47806, CVE-2025-47807 and CVE-2025-47808
- python3-jinja2: Fix CVE-2024-56201, CVE-2024-56326 and CVE-2025-27516
- libxml2: Fix CVE-2025-9714
- libxslt: Fix CVE-2025-7424

- lz4: Fix [CVE-2025-62813](#)
- openssl: Fix [CVE-2025-9230](#) and [CVE-2025-9232](#)
- pulseaudio: Ignore [CVE-2024-11586](#)
- python3: Fix [CVE-2024-6345](#), [CVE-2025-47273](#) and [CVE-2025-59375](#)
- qemu: Fix [CVE-2024-8354](#)
- tiff: Fix [CVE-2025-8961](#), [CVE-2025-9165](#) and [CVE-2025-9900](#)
- vim: Fix [CVE-2025-9389](#)

### Fixes in Yocto-4.0.31

- build-appliance-image: Update to kirkstone head revision
- poky.conf: bump version for 4.0.31
- ref-manual/classes.rst: document the `relative_symlinks` class
- ref-manual/classes.rst: gettext: extend the documentation of the class
- ref-manual/variables.rst: document the `CCACHE_DISABLE`, `UNINATIVE_CHECKSUM`, `UNINATIVE_URL`, `USE_NLS`, `REQUIRED_COMBINED_FEATURES`, `REQUIRED_IMAGE_FEATURES`, [REQUIRED\\_MACHINE\\_FEATURES](#) variable
- ref-manual/variables.rst: fix [LAYERDEPENDS](#) description
- dev-manual, test-manual: Update autobuilder output links
- ref-manual/classes.rst: extend the uninative class documentation
- python3: upgrade to 3.10.19
- linux-yocto/5.15: update to v5.15.194
- glibc: : `PTHREAD_COND_INITIALIZER` compatibility with pre-2.41 versions (bug 32786)
- glibc: nptl Use all of `g1_start` and `g_signals`
- glibc: nptl rename `__condvar_quiesce_and_switch_g1`
- glibc: nptl Fix indentation
- glibc: nptl Use a single loop in `pthread_cond_wait` instead of a nested loop
- glibc: Remove `g_refs` from condition variables
- glibc: nptl Remove unnecessary quadruple check in `pthread_cond_wait`
- glibc: nptl Remove unnecessary catch-all-wake in `condvar` group switch
- glibc: nptl Update comments and indentation for new `condvar` implementation
- glibc: pthreads NPTL lost wakeup fix 2
- glibc: Remove partial BZ#25847 backport patches
- vulnerabilities: update `nvdCVE` file name
- migration-guides: add release notes for 4.0.30

- oeqa/sdk/cases/buildcpio.py: use gnu mirror instead of main server
- selftest/cases/meta\_ide.py: use use gnu mirror instead of main server
- conf/bitbake.conf: use gnu mirror instead of main server
- p11-kit: backport fix for handle *USE\_NLS* from master
- systemd: backport fix for handle *USE\_NLS* from master
- glibc: stable 2.35 branch updates
- openssl: upgrade to 3.0.18
- scripts/install-buildtools: Update to 4.0.30
- ref-manual/variables.rst: fix the description of *STAGING\_DIR*
- ref-manual/structure: document the auto.conf file
- dev-manual/building.rst: add note about externalsrc variables absolute paths
- ref-manual/variables.rst: fix the description of *KBUILD\_DEFCONFIG*
- kernel-dev/common.rst: fix the in-tree defconfig description
- test-manual/yocto-project-compatible.rst: fix a typo
- contributor-guide: submit-changes: make "Crediting contributors" part of "Commit your changes"
- contributor-guide: submit-changes: number instruction list in commit your changes
- contributor-guide: submit-changes: reword commit message instructions
- contributor-guide: submit-changes: make the Cc tag follow kernel guidelines
- contributor-guide: submit-changes: align *CC* tag description
- contributor-guide: submit-changes: clarify example with Yocto bug ID
- contributor-guide: submit-changes: fix improper bold string
- libhandy: update git branch name
- python3-jinja2: upgrade to 3.1.6
- vim: upgrade to 9.1.1683

### Known Issues in Yocto-4.0.31

- N/A

### Contributors to Yocto-4.0.31

- Adam Blank
- Aleksandar Nikolic
- Antonin Godard
- Archana Polampalli
- AshishKumar Mishra

- Bruce Ashfield
- Deepesh Varatharajan
- Divya Chellam
- Gyorgy Sarvari
- Hitendra Prajapati
- João Marcos Costa
- Lee Chee Yang
- Paul Barker
- Peter Marko
- Praveen Kumar
- Quentin Schulz
- Rajeshkumar Ramasamy
- Saravanan
- Soumya Sambu
- Steve Sakoman
- Sunil Dora
- Talel BELHAJ SALEM
- Theo GAIGE
- Vijay Anusuri
- Yash Shinde
- Yogita Urade

## Repositories / Downloads for Yocto-4.0.31

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: [kirkstone](#)
- Tag: [yocto-4.0.31](#)
- Git Revision: [073f3bca4c374b03398317e7f445d2440a287741](#)
- Release Artefact: [yocto-docs-073f3bca4c374b03398317e7f445d2440a287741](#)
- sha: [3bfde9b6ad310dd42817509b67f61cd69552f74b2bc5011bd20788fe96d6823b](#)
- Download                      Locations:                      <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.31/yocto-docs-073f3bca4c374b03398317e7f445d2440a287741.tar.bz2>                      <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.31/yocto-docs-073f3bca4c374b03398317e7f445d2440a287741.tar.bz2>

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: kirkstone
- Tag: yocto-4.0.31
- Git Revision: 04b39e5b7eb19498215d85c88a5fffb460fea1eb
- Release Artefact: poky-04b39e5b7eb19498215d85c88a5fffb460fea1eb
- sha: 0ca18ab1ed25c0d77412ba30dbb03d74811756c7c2fe2401940f848a5e734930
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.31/poky-04b39e5b7eb19498215d85c88a5fffb460fea1eb.tar.bz2> <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.31/poky-04b39e5b7eb19498215d85c88a5fffb460fea1eb.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: kirkstone
- Tag: yocto-4.0.31
- Git Revision: 99204008786f659ab03538cd2ae2fd23ed4164c5
- Release Artefact: oecore-99204008786f659ab03538cd2ae2fd23ed4164c5
- sha: aa97bf826ad217b3a5278b4ad60bef4d194f0f1ff617677cf2323d3cc4897687
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.31/oecore-99204008786f659ab03538cd2ae2fd23ed4164c5.tar.bz2> <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.31/oecore-99204008786f659ab03538cd2ae2fd23ed4164c5.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: kirkstone
- Tag: yocto-4.0.31
- Git Revision: 3b2df00345b46479237fe0218675a818249f891c
- Release Artefact: meta-yocto-3b2df00345b46479237fe0218675a818249f891c
- sha: 630e99e0f515bab8a316b2e32aff1352b4404f15aa087e8821b84093596a08ce
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.31/meta-yocto-3b2df00345b46479237fe0218675a818249f891c.tar.bz2> <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.31/meta-yocto-3b2df00345b46479237fe0218675a818249f891c.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.31
- Git Revision: 87c22abb1f11be430caf4372e6b833dc7d77564e

- Release Artefact: meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e
- sha: f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.31/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2> <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.31/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.31
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.31/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2> <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.31/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.31
- Git Revision: 8e2d1f8de055549b2101614d85454fcd1d0f94b2
- Release Artefact: bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2
- sha: fad4e7699bae62082118e89785324b031b0af0743064caee87c91ba28549afb0
- Download Locations: <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.31/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2> <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.31/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

## 17.11.34 Release notes for Yocto-4.0.32 (Kirkstone)

### Security Fixes in Yocto-4.0.32

- bind: Fix CVE-2025-8677, CVE-2025-40778 and CVE-2025-40780
- binutils: Fix CVE-2025-11412 and CVE-2025-11413
- curl: Ignore CVE-2025-10966
- elfutils: Fix CVE-2025-1376 and CVE-2025-1377
- gnutls: Fix CVE-2025-9820
- go: Fix CVE-2024-24783, CVE-2025-58187, CVE-2025-58189, CVE-2025-61723 and CVE-2025-61724

- libarchive: Fix CVE-2025-60753
- libarchive: Fix 2 security issue (<https://github.com/libarchive/libarchive/pull/2753> and <https://github.com/libarchive/libarchive/pull/2768>)
- libpng: Fix CVE-2025-64505, CVE-2025-64506, CVE-2025-64720, CVE-2025-65018 and CVE-2025-66293
- libxml2: Fix CVE-2025-7425
- musl: Fix CVE-2025-26519
- openssh: Fix CVE-2025-61984 and CVE-2025-61985
- python3-idna: Fix CVE-2024-3651
- python3-urllib3: Fix CVE-2024-37891
- python3: fix CVE-2025-6075
- ruby: Fix CVE-2024-35176, CVE-2024-39908 and CVE-2024-41123
- rust-cross-canadian: Ignore CVE-2024-43402
- u-boot: Fix CVE-2024-42040
- wpa-suplicant: Fix CVE-2025-24912
- xserver-xorg: Fix CVE-2025-62229, CVE-2025-62230 and CVE-2025-62231
- xwayland: Fix CVE-2025-62229, CVE-2025-62230 and CVE-2025-62231

### Fixes in Yocto-4.0.32

- babeltrace2: fetch with https protocol
- bind: upgrade to 9.18.41
- build-appliance-image: Update to kirkstone head revision
- dev-manual/layers.rst: document "bitbake-layers show-machines"
- dev-manual/new-recipe.rst: replace 'bitbake -e' with 'bitbake-getvar'
- dev-manual/new-recipe.rst: typo, "whith" -> "which"
- dev-manual/new-recipe.rst: update "recipetool -h" output
- dev-manual: debugging: use bitbake-getvar in Viewing Variable Values section
- documentation: link to the Releases page on yoctoproject.org instead of wiki
- efibootmgr: update [SRC\\_URI](#) branch
- flac: patch seeking bug
- goarch.bbclass: do not leak [TUNE\\_FEATURES](#) into crosssdk task signatures
- kernel-dev: add disable config example
- kernel-dev: common: migrate bitbake -e to bitbake-getvar
- libmicrohttpd: disable experimental code by default

- migration-guides: add release notes for 4.0.31
- oe-build-perf-report: relax metadata matching rules
- overview-manual: migrate to SVG + fix typo
- poky.conf: bump version for 4.0.32
- python3-urllib3: upgrade to 1.26.20
- recipes: Don't use ftp.gnome.org
- ref-manual: variables: migrate the *OVERRIDES* note to bitbake-getvar
- systemd-bootchart: update *SRC\_URI* branch
- xf86-video-intel: correct *SRC\_URI* as freedesktop anongit is down

### Known Issues in Yocto-4.0.32

- N/A

### Contributors to Yocto-4.0.32

Thanks to the following people who contributed to this release:

- Alexander Kanavin
- Archana Polampalli
- Divya Chellam
- Gyorgy Sarvari
- Hitendra Prajapati
- Hongxu Jia
- Jason Schonberg
- Lee Chee Yang
- Peter Marko
- Praveen Kumar
- Quentin Schulz
- Richard Purdie
- Robert P. J. Day
- Ross Burton
- Saquib Iltaf
- Soumya Sambu
- Steve Sakoman
- Vijay Anusuri
- Walter Werner SCHNEIDER



## Repositories / Downloads for Yocto-4.0.32

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.32`
- Git Revision: `4b9df539fa06fb19ed8b51ef2d46e5c56779de81`
- Release Artefact: `yocto-docs-4b9df539fa06fb19ed8b51ef2d46e5c56779de81`
- sha: `70ee2caf576683c5f31ac5a592cde1c0650ece25cfd5ff3cc7eedf531575611`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.32/yocto-docs-4b9df539fa06fb19ed8b51ef2d46e5c56779de81.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.32/yocto-docs-4b9df539fa06fb19ed8b51ef2d46e5c56779de81.tar.bz2>

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.32`
- Git Revision: `2c05660b21c7cc1082aeac8b75d8a2d82e249f63`
- Release Artefact: `poky-2c05660b21c7cc1082aeac8b75d8a2d82e249f63`
- sha: `d7a55a18a597a7b140a81586b7ca6379c208ebbb3285de36c48fde10882947d8`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.32/poky-2c05660b21c7cc1082aeac8b75d8a2d82e249f63.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.32/poky-2c05660b21c7cc1082aeac8b75d8a2d82e249f63.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.32`
- Git Revision: `2ed3f8b938579dbbb804e04c45a968cc57761db7`
- Release Artefact: `oecore-2ed3f8b938579dbbb804e04c45a968cc57761db7`
- sha: `11b9632586dfbf3f0ef69eca2014a8002f25ca8d53cfe9424e27361ba3a20831`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.32/oecore-2ed3f8b938579dbbb804e04c45a968cc57761db7.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.32/oecore-2ed3f8b938579dbbb804e04c45a968cc57761db7.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>

- Branch: `kirkstone`

- Tag: `yocto-4.0.32`

- Git Revision: `77b40877c179ea3ce5c37c7ba1831e9c0e289266`

- Release Artefact: `meta-yocto-77b40877c179ea3ce5c37c7ba1831e9c0e289266`

- sha: `e908d42690881cd6e07b9ca18a21eb8761a0ec72d940b12905622e75ba913974`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.32/meta-yocto-77b40877c179ea3ce5c37c7ba1831e9c0e289266.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.32/meta-yocto-77b40877c179ea3ce5c37c7ba1831e9c0e289266.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>

- Branch: `kirkstone`

- Tag: `yocto-4.0.32`

- Git Revision: `87c22abb1f11be430caf4372e6b833dc7d77564e`

- Release Artefact: `meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e`

- sha: `f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.32/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.32/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>

- Branch: `kirkstone`

- Tag: `yocto-4.0.32`

- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`

- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.32/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.32/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.32
- Git Revision: 8e2d1f8de055549b2101614d85454fcd1d0f94b2
- Release Artefact: bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2
- sha: fad4e7699bae62082118e89785324b031b0af0743064caee87c91ba28549afb0
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.32/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.32/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

### 17.11.35 Release notes for Yocto-4.0.33 (Kirkstone)

#### Security Fixes in Yocto-4.0.33

- binutils: Fix CVE-2025-1181, CVE-2025-11494, CVE-2025-11839 and CVE-2025-11840
- cups: Fix CVE-2025-58436 and CVE-2025-61915
- curl: Fix CVE-2025-14017, CVE-2025-15079 and CVE-2025-15224
- dropbear: Fix CVE-2019-6111
- glib-2.0: Fix CVE-2025-13601, CVE-2025-14087 and CVE-2025-14512
- gnupg: Fix CVE-2025-68973
- go: Fix CVE-2023-39323, CVE-2025-61727 and CVE-2025-61729
- go: Fix CVE-2025-58187 (update patch)
- grub: Fix CVE-2025-61661, CVE-2025-61662, CVE-2025-61663 and CVE-2025-61664
- libarchive: Fix CVE-2025-60753 (update patch)
- libpcap: Fix CVE-2025-11961 and CVE-2025-11964
- libsoup: fix CVE-2025-12105

- libxslt: Fix [CVE-2025-11731](#)
- python3: Fix [CVE-2025-13836](#)
- python3-urllib3: Fix [CVE-2025-66418](#)
- qemu: Fix [CVE-2025-12464](#)
- qemu: Ignore [CVE-2025-54566](#) and [CVE-2025-54567](#)
- rsync: Fix [CVE-2025-10158](#)
- util-linux: Fix [CVE-2025-14104](#)

### Fixes in Yocto-4.0.33

- build-appliance-image: Update to kirkstone head revision
- contributor-guide/recipe-style-guide.rst: explain difference between layer and recipe license(s)
- cross.bbclass: Propagate dependencies to outhash
- cups: allow unknown directives in conf files
- docs: Add a new "Security" section
- oeqa: Use 2.14 release of cpio instead of 2.13
- overview-manual/yp-intro.rst: change removed ECOSYSTEM to ABOUT
- overview-manual/yp-intro.rst: fix SDK type in bullet list
- overview-manual/yp-intro.rst: link to YP members and participants
- overview-manual: convert YP-flow-diagram.png to SVG
- poky.conf: Bump version for 4.0.33 release
- pseudo: Upgrade to 1.9.2+git125b020dd2
- ref-manual/classes.rst: document the image-container class
- ref-manual/release-process.rst: add a "Development Cycle" section
- ref-manual/svg/releases.svg: mark styhead and walmnascar EOL
- ref-manual/svg/releases.svg: mark whinlatter as current release
- ref-manual/variables.rst: document the [CCACHE\\_TOP\\_DIR](#) variable
- scripts/install-buildtools: Update to 4.0.31
- test-manual/ptest.rst: detail the exit code and output requirements

### Known Issues in Yocto-4.0.33

- N/A

## Contributors to Yocto-4.0.33

- Aleksandar Nikolic
- Antonin Godard
- Changqing Li
- Deepesh Varatharajan
- Hitendra Prajapati
- Jiaying Song
- Kai Kang
- Khem Raj
- Libo Chen
- Liyin Zhang
- Martin Jansa
- Mingli Yu
- Paul Barker
- Peter Marko
- Richard Purdie
- Robert Yang
- Vijay Anusuri
- Yash Shinde

## Repositories / Downloads for Yocto-4.0.33

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.33`
- Git Revision: `6799b1be5d48f4bf5dcd0b16c2dbc2e297d4ecd9`
- Release Artefact: `yocto-docs-6799b1be5d48f4bf5dcd0b16c2dbc2e297d4ecd9`
- sha: `42a0eb89c8f87a9a966aecb8265f463486d4383cb67d1e67382ddf9d4d7f88b5`
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.33/yocto-docs-6799b1be5d48f4bf5dcd0b16c2dbc2e297d4ecd9.tar.bz2>
  - <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.33/yocto-docs-6799b1be5d48f4bf5dcd0b16c2dbc2e297d4ecd9.tar.bz2>

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.33`
- Git Revision: `ff118ede826a9ae45eb35025a5f7f612880fba01`
- Release Artefact: `poky-ff118ede826a9ae45eb35025a5f7f612880fba01`
- sha: `2a8c24406fa96fc52728a96f25136a3fd7ee652eea6e12319a6b7c0457ccfd`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.33/poky-ff118ede826a9ae45eb35025a5f7f612880fba01.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.33/poky-ff118ede826a9ae45eb35025a5f7f612880fba01.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.33`
- Git Revision: `036f76ea35c49a78d612093dcd8eb1fac7ded8d7`
- Release Artefact: `oecore-036f76ea35c49a78d612093dcd8eb1fac7ded8d7`
- sha: `fc180ff224529fd73a7aec4a4cf5beb40fba17646ee694715cf603baba26610c`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.33/oecore-036f76ea35c49a78d612093dcd8eb1fac7ded8d7.tar.bz2>  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.33/oecore-036f76ea35c49a78d612093dcd8eb1fac7ded8d7.tar.bz2>

#### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>
- Branch: `kirkstone`
- Tag: `yocto-4.0.33`
- Git Revision: `677379f21941363d50f9d946963542b4ccb7e27c`
- Release Artefact: `meta-yocto-677379f21941363d50f9d946963542b4ccb7e27c`
- sha: `90f52c406f4e69748b8d73eee07b8a1247d19cc29f4893174f110a034b10415f`
- Download Locations:  
<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.33/meta-yocto-677379f21941363d50f9d946963542b4ccb7e27c.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.33/meta-yocto-677379f21941363d50f9d946963542b4ccb7e27c.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: kirkstone
- Tag: yocto-4.0.33
- Git Revision: 87c22abb1f11be430caf4372e6b833dc7d77564e
- Release Artefact: meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e
- sha: f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.33/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.33/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: kirkstone
- Tag: yocto-4.0.33
- Git Revision: d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.33/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.33/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.33
- Git Revision: 8e2d1f8de055549b2101614d85454fcd1d0f94b2
- Release Artefact: bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2
- sha: fad4e7699bae62082118e89785324b031b0af0743064caee87c91ba28549afb0

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.33/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.33/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

### 17.11.36 Release notes for Yocto-4.0.34 (Kirkstone)

#### Security Fixes in Yocto-4.0.34

- avahi: Fix CVE-2026-24401, CVE-2025-68276, CVE-2025-68468 and CVE-2025-68471
- bind: Fix CVE-2025-13878
- expat: Fix CVE-2026-24515 and CVE-2026-25210
- ffmpeg: Ignore CVE-2025-25468 and CVE-2025-25469
- glib-2.0: Fix CVE-2026-0988, CVE-2026-1484, CVE-2026-1485 and CVE-2026-1489
- glibc: Fix CVE-2025-15281, CVE-2026-0861 and CVE-2026-0915
- harfbuzz: Ignore CVE-2026-22693
- inetutils: Fix CVE-2026-24061
- libpng: Fix CVE-2026-22695, CVE-2026-22801 and CVE-2026-25646
- libtasn1: Fix CVE-2025-13151
- libxml2: Fix CVE-2026-0990 and CVE-2026-0992
- linux-yocto/5.15: Fix CVE-2022-49465, CVE-2023-54207, CVE-2025-22058, CVE-2025-40040, CVE-2025-40149, CVE-2025-40164, CVE-2025-68211, CVE-2025-68340, CVE-2025-68365, CVE-2025-68725, CVE-2025-68817, CVE-2025-71147, CVE-2025-71154, CVE-2025-71162, CVE-2025-71163, CVE-2026-22976, CVE-2026-22977, CVE-2026-22978, CVE-2026-22980, CVE-2026-22982, CVE-2026-22984, CVE-2026-22990, CVE-2026-22991, CVE-2026-22992, CVE-2026-22997, CVE-2026-22998, CVE-2026-22999, CVE-2026-23060, CVE-2026-23061, CVE-2026-23063, CVE-2026-23064, CVE-2026-23076, CVE-2026-23078, CVE-2026-23080, CVE-2026-23083, CVE-2026-23084, CVE-2026-23085, CVE-2026-23087, CVE-2026-23089, CVE-2026-23090, CVE-2026-23091, CVE-2026-23093, CVE-2026-23095, CVE-2026-23096, CVE-2026-23097, CVE-2026-23119, CVE-2026-23120, CVE-2026-23121, CVE-2026-23124, CVE-2026-23125, CVE-2026-23133, CVE-2026-23146, CVE-2026-23150, CVE-2026-23164, CVE-2026-23167 and CVE-2026-23170
- openssl: Fix CVE-2025-15467, CVE-2026-22795, CVE-2026-22796, CVE-2025-68160, CVE-2025-69418, CVE-2025-69419, CVE-2025-69420 and CVE-2025-69421
- python3: Fix CVE-2025-12084 and CVE-2025-13837
- vim: Ignore CVE-2025-66476
- zlib: Ignore CVE-2026-22184



### Fixes in Yocto-4.0.34

- bind: Upgrade to 9.18.44
- build-appliance-image: Update to kirkstone head revision
- classes/buildhistory: Do not sign buildhistory commits
- dev-manual/packages.rst: fix example recipe version
- dev-manual/packages.rst: pr server: fix and explain why r0.X increments on [SRCREV](#) change
- dev-manual/packages.rst: rename r0.0 to r0 when [PR](#) server is not enabled
- glibc: stable 2.35 branch updates
- linux-yocto/5.15: update to v5.15.199
- migration-guides: add release notes for 4.0.32
- openssl: upgrade to 3.0.19
- poky.conf: Bump version for 4.0.34 release
- poky.conf: add fedora-41, debian-12, rocky-8&9 to [SANITY\\_TESTED\\_DISTROS](#)
- pseudo: Update to 1.9.3+git43cbd8fb49
- ref-manual/classes.rst: fix broken links to U-Boot documentation
- ref-manual/system-requirements.rst: update untested distros
- scripts/install-buildtools: Update to 4.0.32
- u-boot: move CVE patch out of u-boot-common.inc
- what-i-wish-id-known.rst: replace figure by the new SVG

### Known Issues in Yocto-4.0.34

- N/A

### Contributors to Yocto-4.0.34

- Aleksandar Nikolic
- Amaury Couderc
- Ankur Tyagi
- Antonin Godard
- Bruce Ashfield
- Fabio Berton
- Hugo SIMELIERE
- Lee Chee Yang
- Michael Opdenacker
- Paul Barker

- Peter Marko
- Richard Purdie
- Scott Murray
- Vijay Anusuri
- Yoann Congal

## Repositories / Downloads for Yocto-4.0.34

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.34`
- Git Revision: `7c348dd67cfd169b1a56bf969606b03dcc76c56`
- Release Artefact: `yocto-docs-7c348dd67cfd169b1a56bf969606b03dcc76c56`
- sha: `0677fc3aee3c936599f3bcffbe16792494058bd3506ca3ab1697ceac1822829b`
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.34/yocto-docs-7c348dd67cfd169b1a56bf969606b03dcc76c56.tar.bz2>
  - <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.34/yocto-docs-7c348dd67cfd169b1a56bf969606b03dcc76c56.tar.bz2>

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.34`
- Git Revision: `8334e82e1d85e50557bd3da64054fc9e3eafc495`
- Release Artefact: `poky-8334e82e1d85e50557bd3da64054fc9e3eafc495`
- sha: `74fcc57d1dd3bb0c6ef77bfaeca7504f393e705a55149cf52d4b61981c9c387`
- Download Locations:
  - <https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.34/poky-8334e82e1d85e50557bd3da64054fc9e3eafc495.tar.bz2>
  - <https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.34/poky-8334e82e1d85e50557bd3da64054fc9e3eafc495.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`

- Tag: `yocto-4.0.34`
- Git Revision: `7b6c9faa301a6d058ca34e230586f6a81ffa3ffb`
- Release Artefact: `oecore-7b6c9faa301a6d058ca34e230586f6a81ffa3ffb`
- sha: `375a22e3e229064749e78c80c44cde95adcedd26df76045fccefa3a9d3fa14ad`
- Download Locations:  
  
`https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.34/oecore-7b6c9faa301a6d058ca34e230586f6a81ffa3ffb.tar.bz2`  
  
`https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.34/oecore-7b6c9faa301a6d058ca34e230586f6a81ffa3ffb.tar.bz2`

#### meta-yocto

- Repository Location: `https://git.yoctoproject.org/meta-yocto`
- Branch: `kirkstone`
- Tag: `yocto-4.0.34`
- Git Revision: `1d3874a383023a5e2433e0fcfd87ac5d1e6d341d`
- Release Artefact: `meta-yocto-1d3874a383023a5e2433e0fcfd87ac5d1e6d341d`
- sha: `baf48bbe1f29686d502c0c6f311c7723b0a18f08e7efbf89c150589102285dbe`
- Download Locations:  
  
`https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.34/meta-yocto-1d3874a383023a5e2433e0fcfd87ac5d1e6d341d.tar.bz2`  
  
`https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.34/meta-yocto-1d3874a383023a5e2433e0fcfd87ac5d1e6d341d.tar.bz2`

#### meta-mingw

- Repository Location: `https://git.yoctoproject.org/meta-mingw`
- Branch: `kirkstone`
- Tag: `yocto-4.0.34`
- Git Revision: `87c22abb1f11be430caf4372e6b833dc7d77564e`
- Release Artefact: `meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e`
- sha: `f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8`
- Download Locations:  
  
`https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.34/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2`  
  
`https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.34/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2`

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `kirkstone`
- Tag: `yocto-4.0.34`
- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- Release Artefact: `meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`
- sha: `c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.34/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.34/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: `2.0`
- Tag: `yocto-4.0.34`
- Git Revision: `8e2d1f8de055549b2101614d85454fcd1d0f94b2`
- Release Artefact: `bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2`
- sha: `fad4e7699bae62082118e89785324b031b0af0743064caee87c91ba28549afb0`
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.34/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.34/bitbake-8e2d1f8de055549b2101614d85454fcd1d0f94b2.tar.bz2>

## 17.11.37 Release notes for Yocto-4.0.35 (Kirkstone)

### Security Fixes in Yocto-4.0.35

- alsa-lib: Fix CVE-2026-25068
- busybox: Fix CVE-2025-60876
- curl: Fix CVE-2025-14524, CVE-2026-1965, CVE-2026-3783 and CVE-2026-3784
- ffmpeg: Fix CVE-2025-10256
- gdk-pixbuf: Fix CVE-2025-6199
- inetutils: Fix CVE-2026-28372
- libarchive: Fix CVE-2026-4111
- libpam: Fix CVE-2024-10963

- linux-yocto/5.15: Fix [CVE-2025-40082](#), [CVE-2025-68358](#), [CVE-2025-71089](#), [CVE-2025-71220](#), [CVE-2025-71222](#), [CVE-2025-71232](#), [CVE-2025-71233](#), [CVE-2025-71235](#), [CVE-2025-71236](#), [CVE-2025-71237](#), [CVE-2025-71238](#), [CVE-2026-23111](#), [CVE-2026-23112](#), [CVE-2026-23169](#), [CVE-2026-23190](#), [CVE-2026-23193](#), [CVE-2026-23198](#), [CVE-2026-23202](#), [CVE-2026-23206](#), [CVE-2026-23209](#), [CVE-2026-23216](#), [CVE-2026-23221](#), [CVE-2026-23222](#), [CVE-2026-23228](#), [CVE-2026-23229](#), [CVE-2026-23231](#), [CVE-2026-23234](#), [CVE-2026-23235](#), [CVE-2026-23236](#), [CVE-2026-23237](#) and [CVE-2026-23238](#)
- ncurses: Fix [CVE-2025-69720](#)
- python3: Fix [CVE-2024-6923](#), [CVE-2025-15282](#), [CVE-2025-59375](#), [CVE-2026-0865](#), [CVE-2026-24515](#) and [CVE-2026-25210](#)
- python3-pip: Fix [CVE-2026-1703](#)
- python3-pyopenssl: Fix [CVE-2026-27448](#) and [CVE-2026-27459](#)
- sqlite3: Fix [CVE-2025-70873](#)
- tiff: Fix [CVE-2025-61143](#) and [CVE-2025-61144](#)
- vim: Fix [CVE-2026-25749](#), [CVE-2026-26269](#), [CVE-2026-28418](#), [CVE-2026-28419](#) and [CVE-2026-33412](#)

### Fixes in Yocto-4.0.35

- bitbake: tests/fetch: Avoid using git protocol in tests
- build-appliance-image: Update to kirkstone head revision
- contributor-guide/submit-changes.rst: Added missing word
- create-pull-request: Keep commit hash to be pulled in cover email
- createrepo-c: Fix createrepo-c-native build on GCC14 hosts (e.g. Fedora 41)
- gtk+3: fix incompatible-pointer-types errors for native build on Fedora 41
- libcomps: Fix libcomps-native build on GCC14 hosts (e.g. Fedora 41)
- libpam: re-add missing libgen include
- libtheora: set *CVE\_PRODUCT*
- linux-yocto/5.15: update to v5.15.201
- lsb.py: strip ' from os-release file
- migration-guide: add release notes for 4.0.33 4.0.34
- oeqa/manual: Default to https git protocol for YP/OE repos
- oeqa/sdk: Default to https git protocol for YP/OE repos
- oeqa/selftest/git-submodule-test: Default to https git protocol for YP/OE repos
- overview-manual: escape wildcard in inline markup
- poky.conf: Bump version for 4.0.35 release
- python3: upgrade to 3.10.20
- README.OE-Core: update contributor links and add kirkstone prefix

- recipes: Default to https git protocol for YP/OE repos
- recipetool: Recognise <https://git>. as git urls
- ref-manual/system-requirements.rst: update end-of-life distros
- scripts/install-buildtools: Update to 4.0.34
- scripts: Default to https git protocol for YP/OE repos
- selftest/scripts: Update old git protocol references
- tcl: skip http11 tests
- tiff: set status of CVE-2025-61145 as fixed by patch for [CVE-2025-8961](#)
- tzdata,tzcode-native: Upgrade to 2026a

### Known Issues in Yocto-4.0.35

- N/A

### Contributors to Yocto-4.0.35

- Aleksandar Nikolic
- Antonin Godard
- Bruce Ashfield
- Fabien Thomas
- Hitendra Prajapati
- Jinfeng Wang
- Ken Kurematsu
- Kristiyan Chakarov
- Lee Chee Yang
- Martin Jansa
- Paul Barker
- Peter Marko
- Richard Purdie
- Ross Burton
- Shaik Moin
- Vijay Anusuri
- Yanis BINARD
- Yoann Congal

## Repositories / Downloads for Yocto-4.0.35

### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: `kirkstone`
- Tag: `yocto-4.0.35`
- Git Revision: `ce6734c68649739c635675a133fa77edb9865028`
- Release Artefact: `yocto-docs-ce6734c68649739c635675a133fa77edb9865028`
- sha: `ddb6fac4d257f4f76836055cafad529729e99c293d3b8d3dabef926fad5e725f`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.35/yocto-docs-ce6734c68649739c635675a133fa77edb9865028.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.35/yocto-docs-ce6734c68649739c635675a133fa77edb9865028.tar.bz2>

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `kirkstone`
- Tag: `yocto-4.0.35`
- Git Revision: `93431249a6260da7bd29ee3ca32145d89e5b8259`
- Release Artefact: `poky-93431249a6260da7bd29ee3ca32145d89e5b8259`
- sha: `a8e95213248c5400276611754f2c98b8d8972e166bdf41433c45fcdd2bf668cb`
- Download Locations:  
  
<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.35/poky-93431249a6260da7bd29ee3ca32145d89e5b8259.tar.bz2>  
  
<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.35/poky-93431249a6260da7bd29ee3ca32145d89e5b8259.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `kirkstone`
- Tag: `yocto-4.0.35`
- Git Revision: `51259c7e933a2ac8ebc01604d6e65607b76b7b56`
- Release Artefact: `oecore-51259c7e933a2ac8ebc01604d6e65607b76b7b56`
- sha: `2cd531e2a107849e7a452e71e41f22b42160979066e10d0661e97acfab125b1f`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.35/oecore-51259c7e933a2ac8ebc01604d6e65607b76b7b56.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.35/oecore-51259c7e933a2ac8ebc01604d6e65607b76b7b56.tar.bz2>

### meta-yocto

- Repository Location: <https://git.yoctoproject.org/meta-yocto>

- Branch: `kirkstone`

- Tag: `yocto-4.0.35`

- Git Revision: `34e3c9a19b8b955116109a2e9528966db3fced37`

- Release Artefact: `meta-yocto-34e3c9a19b8b955116109a2e9528966db3fced37`

- sha: `18da6dbb745d5e4e42a93527c36751778155e3762728b0b1020b890480402dde`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.35/meta-yocto-34e3c9a19b8b955116109a2e9528966db3fced37.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.35/meta-yocto-34e3c9a19b8b955116109a2e9528966db3fced37.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>

- Branch: `kirkstone`

- Tag: `yocto-4.0.35`

- Git Revision: `87c22abb1f11be430caf4372e6b833dc7d77564e`

- Release Artefact: `meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e`

- sha: `f0bc4873e2e0319fb9d6d6ab9b98eb3f89664d4339a167d2db6a787dd12bc1a8`

- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.35/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.35/meta-mingw-87c22abb1f11be430caf4372e6b833dc7d77564e.tar.bz2>

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>

- Branch: `kirkstone`

- Tag: `yocto-4.0.35`

- Git Revision: `d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a`



- Release Artefact: meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a
- sha: c386f59f8a672747dc3d0be1d4234b6039273d0e57933eb87caa20f56b9cca6d
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.35/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.35/meta-gplv2-d2f8b5cdb285b72a4ed93450f6703ca27aa42e8a.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 2.0
- Tag: yocto-4.0.35
- Git Revision: 7fd0197fd5fedd23cc885b5e7e816d86a392fdf9
- Release Artefact: bitbake-7fd0197fd5fedd23cc885b5e7e816d86a392fdf9
- sha: 6c01ff2b4b0060ef3d6d3f1fc11690094b22865af4989946544d08d74b473ec9
- Download Locations:

<https://downloads.yoctoproject.org/releases/yocto/yocto-4.0.35/bitbake-7fd0197fd5fedd23cc885b5e7e816d86a392fdf9.tar.bz2>

<https://mirrors.edge.kernel.org/yocto/yocto/yocto-4.0.35/bitbake-7fd0197fd5fedd23cc885b5e7e816d86a392fdf9.tar.bz2>

## 17.12 Release 3.4 (honister)

### 17.12.1 Migration notes for 3.4 (honister)

This section provides migration information for moving to the Yocto Project 3.4 Release (codename "honister") from the prior release.

#### Override syntax changes

In this release, the `:` character replaces the use of `_` to refer to an override, most commonly when making a conditional assignment of a variable. This means that an entry like:

```
SRC_URI_qemux86 = "file://somefile"
```

now becomes:

```
SRC_URI:qemux86 = "file://somefile"
```

since `qemux86` is an override. This applies to any use of override syntax, so the following:

```
SRC_URI_append = " file://somefile"
SRC_URI_append_qemux86 = " file://somefile2"
SRC_URI_remove_qemux86-64 = "file://somefile3"
SRC_URI_prepend_qemuarm = "file://somefile4 "
FILES_${PN}-ptest = "${bindir}/xyz"
IMAGE_CMD_tar = "tar"
BASE_LIB_tune-cortexa76 = "lib"
SRCREV_pn-bash = "abc"
BB_TASK_NICE_LEVEL_task-testimage = '0'
```

would now become:

```
SRC_URI:append = " file://somefile"
SRC_URI:append:qemux86 = " file://somefile2"
SRC_URI:remove:qemux86-64 = "file://somefile3"
SRC_URI:prepend:qemuarm = "file://somefile4 "
FILES:${PN}-ptest = "${bindir}/xyz"
IMAGE_CMD:tar = "tar"
BASE_LIB:tune-cortexa76 = "lib"
SRCREV:pn-bash = "abc"
BB_TASK_NICE_LEVEL:task-testimage = '0'
```

This also applies to [variable queries to the datastore](#), for example using `getVar` and similar so `d.getVar("RDEPENDS_${PN}")` becomes `d.getVar("RDEPENDS:${PN}")`.

Whilst some of these are fairly obvious such as [MACHINE](#) and [DISTRO](#) overrides, some are less obvious, for example the packaging variables such as [RDEPENDS](#), [FILES](#) and so on taking package names (e.g. `${PN}`, `${PN}-ptest`) as overrides. These overrides are not always in [OVERRIDES](#) but applied conditionally in specific contexts such as packaging. `task-<taskname>` is another context specific override, the context being specific tasks in that case. Tune overrides are another special case where some code does use them as overrides but some does not. We plan to try and make the tune code use overrides more consistently in the future.

There are some variables which do not use override syntax which include the suffix to variables in `layer.conf` files such as [BBFILE\\_PATTERN](#), [SRCREV\\_xxx](#) where `xxx` is a name from [SRC\\_URI](#) and [PREFERRED\\_VERSION\\_xxx](#). In particular, `layer.conf` suffixes may be the same as a [DISTRO](#) override causing some confusion. We do plan to try and improve consistency as these issues are identified.

To help with migration of layers, a script has been provided in OE-Core. Once configured with the overrides used by a layer, this can be run as:

```
<oe-core>/scripts/contrib/convert-overrides.py <layerdir>
```

#### Nota

Please read the notes in the script as it isn't entirely automatic and it isn't expected to handle every case. In particular, it needs to be told which overrides the layer uses (usually machine and distro names/overrides) and

the result should be carefully checked since it can be a little enthusiastic and will convert references to `_append`, `_remove` and `_prepend` in function and variable names.

For reference, this conversion is important as it allows BitBake to more reliably determine what is an override and what is not, as underscores are also used in variable names without intending to be overrides. This should allow us to proceed with other syntax improvements and simplifications for usability. It also means BitBake no longer has to guess and maintain large lookup lists just in case e.g. `functionname` in `my_functionname` is an override, and thus should improve efficiency.

## New host dependencies

The `lz4c`, `pzstd` and `zstd` commands are now required to be installed on the build host to support LZ4 and Zstandard compression functionality. These are typically provided by `lz4` and `zstd` packages in most Linux distributions. Alternatively they are available as part of *buildtools* tarball if your distribution does not provide them. For more information see *Pacchetti Richiesti per l'Host di Build*.

## Removed recipes

The following recipes have been removed in this release:

- `assimp`: problematic from a licensing perspective and no longer needed by anything else
- `clutter-1.0`: legacy component moved to meta-gnome
- `clutter-gst-3.0`: legacy component moved to meta-gnome
- `clutter-gtk-1.0`: legacy component moved to meta-gnome
- `cogl-1.0`: legacy component moved to meta-gnome
- `core-image-clutter`: removed along with clutter
- `linux-yocto`: removed version 5.4 recipes (5.14 and 5.10 still provided)
- `mklibs-native`: not actively tested and upstream mklibs still requires Python 2
- `mx-1.0`: obsolete (last release 2012) and isn't used by anything in any known layer
- `packagegroup-core-clutter`: removed along with clutter

## Removed classes

- `clutter`: moved to meta-gnome along with clutter itself
- `image-mklibs`: not actively tested and upstream mklibs still requires Python 2
- `meta`: no longer useful. Recipes that need to skip installing packages should inherit *nopackages* instead.

## Prelinking disabled by default

Recent tests have shown that prelinking works only when PIE is not enabled (see [here](#)), and as PIE is both a desirable security feature, and the only configuration provided and tested by the Yocto Project, there is simply no sense in continuing to enable prelink.

There's also a concern that no one is maintaining the code, and there are open bugs (including [this serious one](#)). Given that prelink does intricate address arithmetic and rewriting of binaries the best option is to disable the feature. It is recommended that you consider disabling this feature in your own configuration if it is currently enabled.

### Virtual runtime provides

Recipes shouldn't use the `virtual/` string in *RPROVIDES* and *RDEPENDS* --- it is confusing because `virtual/` has no special meaning in *RPROVIDES* and *RDEPENDS* (unlike in the corresponding build-time *PROVIDES* and *DEPENDS*).

### Tune files moved to architecture-specific directories

The tune files found in `conf/machine/include` have now been moved into their respective architecture name directories under that same location; e.g. x86 tune files have moved into an `x86` subdirectory, MIPS tune files have moved into a `mips` subdirectory, etc. The ARM tunes have an extra level (`armv8a`, `armv8m`, etc.) and some have been renamed to make them uniform with the rest of the tunes. See [this commit](#) for reference.

If you have any references to tune files (e.g. in custom machine configuration files) they will need to be updated.

### Extensible SDK host extension

For a normal SDK, some layers append to *TOOLCHAIN\_HOST\_TASK* unconditionally which is fine, until the eSDK tries to override the variable to its own values. Instead of installing packages specified in this variable it uses native recipes instead --- a very different approach. This has led to confusing errors when binaries are added to the SDK but not relocated.

To avoid these issues, a new *TOOLCHAIN\_HOST\_TASK\_ESDK* variable has been created. If you wish to extend what is installed in the host portion of the eSDK then you will now need to set this variable.

### Package/recipe splitting

- `perl-cross` has been split out from the main `perl` recipe to its own `perlcross` recipe for maintenance reasons. If you have `bbappends` for the `perl` recipe then these may need extending.
- The `wayland` recipe now packages its binaries in a `wayland-tools` package rather than putting them into `wayland-dev`.
- Xwayland has been split out of the `xserver-xorg` tree and thus is now in its own `xwayland` recipe. If you need Xwayland in your image then you may now need to add it explicitly.
- The `rpm` package no longer has `rpm-build` in its *RRECOMMENDS*; if by chance you still need `rpm` package building functionality in your image and you have not already done so then you should add `rpm-build` to your image explicitly.
- The Python `statistics` standard module is now packaged in its own `python3-statistics` package instead of `python3-misc` as previously.

## Image / SDK generation changes

- Recursive dependencies on the *do\_build* task are now disabled when building SDKs. These are generally not needed; in the unlikely event that you do encounter problems then it will probably be as a result of missing explicit dependencies that need to be added.
- Errors during "complementary" package installation (e.g. for \*-dbg and \*-dev packages) during image construction are no longer ignored. Historically some of these packages had installation problems, that is no longer the case. In the unlikely event that you see errors as a result, you will need to fix the installation/packaging issues.
- When building an image, only packages that will be used in building the image (i.e. the first entry in *PACKAGE\_CLASSES*) will be produced if multiple package types are enabled (which is not a typical configuration). If in your CI system you need to have the original behaviour, use `bitbake --runall build <target>`.
- The `-lic` package is no longer automatically added to *RRECOMMENDS* for every other package when *LICENSE\_CREATE\_PACKAGE* is set to "1". If you wish all license packages to be installed corresponding to packages in your image, then you should instead add the new `lic-pkgs` feature to *IMAGE\_FEATURES*.

## Miscellaneous

- Certificates are now properly checked when BitBake fetches sources over HTTPS. If you receive errors as a result for your custom recipes, you will need to use a mirror or address the issue with the operators of the server in question.
- `avahi` has had its GTK+ support disabled by default. If you wish to re-enable it, set `AVAHI_GTK = "gtk3"` in a `bbappend` for the `avahi` recipe or in your custom distro configuration file.
- Setting the `BUILD_REPRODUCIBLE_BINARIES` variable to "0" no longer uses a strangely old fallback date of April 2011, it instead disables building reproducible binaries as you would logically expect.
- Setting `noexec/nostamp/fakeroot` varflags to any value besides "1" will now trigger a warning. These should be either set to "1" to enable, or not set at all to disable.
- The previously deprecated `COMPRESS_CMD` and `CVE_CHECK_CVE_WHITELIST` variables have been removed. Use *CONVERSION\_CMD* and `CVE_CHECK_WHITELIST` (replaced by *CVE\_CHECK\_IGNORE* in version 4.0) respectively instead.
- The obsolete `oe_machinstall` function previously provided in the *utils* class has been removed. For machine-specific installation it is recommended that you use the built-in override support in the `fetcher` or overrides in general instead.
- The `-P` (`--clear-password`) option can no longer be used with `useradd` and `usermod` entries in *EXTRA\_USERS\_PARAMS*. It was being implemented using a custom patch to the `shadow` recipe which clashed with a `-P` option that was added upstream in `shadow` version 4.9, and in any case is fundamentally insecure. Hardcoded passwords are still supported but they need to be hashed, see examples in *EXTRA\_USERS\_PARAMS*.

## 17.12.2 Release notes for 3.4 (honister)

### New Features / Enhancements in 3.4

- Linux kernel 5.14, glibc 2.34 and ~280 other recipe upgrades
- Switched override character to ':' (replacing '\_') for more robust parsing and improved performance --- see the above migration guide for help
- Rust integrated into core, providing rust support for cross-compilation and SDK
- New *create-spdx* class for creating SPDX SBoM documents
- New recipes: cargo, core-image-ptest-all, core-image-ptest-fast, core-image-weston-sdk, erofs-utils, gcompat, gi-docgen, libmicrohttpd, libseccomp, libstd-rs, perlcross, python3-markdown, python3-pyyaml, python3-smartypants, python3-typogrify, rust, rust-cross, rust-cross-canadian, rust-hello-world, rust-llvm, rust-tools-cross-canadian, rustfmt, xwayland
- Several optimisations to reduce unnecessary task dependencies for faster builds
- seccomp integrated into core, with additional enabling for gnutls, systemd, qemu
- New overlayfs class to help generate overlayfs mount units
- debuginfod support now enabled by default
- Switched several recipes over to using OpenSSL instead of GnuTLS (wpa-supPLICANT, curl, glib-networking) or disable GnuTLS (cups) by default
- Improvements to LTO plugin installation and reproducibility
- Architecture-specific enhancements:
  - glibc: Enable memory tagging for aarch64
  - testimage: remove aarch64 xorg exclusion
  - arch-arm\*: add better support for gcc march extensions
  - tune-cortexm\*: add support for all Arm Cortex-M processors
  - tune-cortexr\*: add support for all Arm Cortex-R processors
  - arch-armv4: Allow -march=armv4
  - qemuarm\*: use virtio graphics
  - baremetal-helloworld: Enable RISC-V 64/32 port
  - ldconfig-native: Add RISC-V support
  - qemuriscv: Enable 4 core emulation
  - Add ARC support in gdb, dpkg, dhcpd
  - conf/machine-sdk: Add ppc64 SDK machine
  - libjpeg-turbo: Handle powerpc64le without Altivec
  - pixman: Handle PowerPC without Altivec
  - mesa: enable gallium Intel drivers when building for x86

- mesa: enable crocus driver for older Intel graphics
- Kernel-related enhancements:
  - Support zstd-compressed modules and *Initramfs* images
  - Allow opt-out of split kernel modules
  - linux-yocto-dev: base *AUTOREV* on specified version
  - kernel-yocto: provide debug / summary information for metadata
  - kernel-uboot: Handle gzip and lzo compression options
  - linux-yocto/5.14: added devupstream support
  - linux-yocto: add vfat to *KERNEL\_FEATURES* when *MACHINE\_FEATURES* include vfat
  - linux-yocto: enable TYPEC\_TPCPI in usbc fragment
- Image-related enhancements:
  - New erofs, erofs-lz4 and erofs-lz4hc image types
  - New squashfs-zst and cpio.zst image types
  - New lic-pkgs *IMAGE\_FEATURES* item to install all license packages
  - Added zsync metadata conversion support
  - Use xargs to set file timestamps for significant (>90%) do\_image speedup
  - Find .ko.gz and .ko.xz kernel modules as well when determining need to run depmod on an image
  - Show formatted error messages instead of tracebacks for systemctl errors
  - No longer ignore installation failures in complementary package installation
  - Remove ldconfig auxiliary cache when not needed
- wic enhancements:
  - Added erofs filesystem support
  - Added `--extra-space` argument to leave extra space after last partition
  - Added `--no-fstab-update` part option to allow using the stock fstab
  - bootimg-efi: added Unified Kernel Image option
  - bootimg-pcbios: use label provided when formatting a DOS partition
- SDK-related enhancements:
  - Enable *do\_populate\_sdk* with multilibs
  - New `SDKPATHINSTALL` variable decouples default install path from built in path to avoid rebuilding *nativesdk* components on e.g. *DISTRO\_VERSION* changes
  - eSDK: Error if trying to generate an eSDK from a multiconfig
  - eSDK: introduce *TOOLCHAIN\_HOST\_TASK\_ESDK* to be used in place of *TOOLCHAIN\_HOST\_TASK* to add components to the host part of the eSDK

- BitBake enhancements:
  - New bitbake-getvar helper command to query a variable value (with history)
  - bitbake-layers: layerindex-fetch: add `--fetchdir` parameter
  - bitbake-layers: show-recipes: add skip reason to output
  - bitbake-diffsigs: sort diff output for consistency
  - Allow setting upstream for local hash equivalence server
  - fetch2/s3: allow to use credentials and switch profile from environment variables
  - fetch2/s3: Add progress handler for S3 cp command
  - fetch2/npm: Support npm archives with missing search directory mode
  - fetch2/npsw: Add support for local tarball and link sources
  - fetch2/svn: Allow peg-revision functionality to be disabled
  - fetch2/wget: verify certificates for HTTPS/FTPS by default
  - fetch2/wget: Enable FTPS
  - prserv: added read-only mode
  - prserv: replaced XML RPC with modern asynrpc implementation
  - Numerous warning/error message improvements
- New *PACKAGECONFIG* options in btrfs-tools, ccache, coreutils, cups, dbus, elfutils, ffmpeg, findutils, glib-2.0, gstreamer1.0-plugins-bad, gstreamer1.0-plugins-base, libarchive, libnotify, libpsl, man-db, mesa, ovmf, parted, prelink, qemu, rpm, shadow, systemd, tar, vim, weston
- u-boot enhancements:
  - Make SPL suffix configurable
  - Make UBOOT\_BINARYNAME configurable
  - Package `extlinux.conf` separately
  - Allow deploying the u-boot DTB
- opensbi: Add support for specifying a device tree
- busybox enhancements:
  - Added tmpdir option into mktemp applet
  - Support mounting swap via labels
  - Enable long options for enabled applets
- Move tune files to architecture subdirectories
- buildstats: log host data on failure separately to task specific file
- buildstats: collect "at interval" and "on failure" logs in the same file
- Ptest enhancements:



- ptest-runner: install script to collect system data on failure
  - Added ptest support to python3-hypothesis, python3-jinja2, python3-markupsafe
  - Enhanced ptest support in lttnng, util-linux, and others
  - New leaner ptest image recipes based upon core-image-minimal
- scripts/contrib/image-manifest: add new script
- Add beginnings of Android target support
- devtool upgrade: rebase override-only patches as well
- devtool: print a warning on upgrades if *PREFERRED\_VERSION* is set
- systemd: set zstd as default compression option
- init-manager-systemd: add a weak VIRTUAL-RUNTIME\_dev\_manager assignment
- Add proper unpack dependency for .zst compressed archives
- util-linux: build chfn and chsh by default
- qemu: use 4 cores in qemu guests
- runqemu: decouple bios and kernel options
- qemu: add a hint on how to enable CPU render nodes when a suitable GPU is absent
- devupstream: Allow support of native class extensions
- Prelinking now disabled in default configuration
- python3: statistics module moved to its own python3-statistics package
- pypi: allow override of PyPI archive name
- Allow global override of golang GO\_DYNLINK
- buildhistory enhancements:
  - Add option to strip path prefix
  - Add output file listing package information
  - Label packages providing per-file dependencies in depends.dot
- New gi-docgen class for GNOME library documentation
- meson.bbclass: Make the default buildtype "debug" if *DEBUG\_BUILD* is 1
- distro\_features\_check: expand with *IMAGE\_FEATURES*
- Add extended packagedata in JSON format
- local.conf.sample: Update sstate mirror entry with new hash equivalence setting
- poky: Use https in default *PREMIRRORS*
- reproducible\_build.bbclass: Enable -Wdate-time
- yocto-check-layer: ensure that all layer dependencies are tested too

- core-image-multilib-example: base on weston, and not sato
- npm.bbclass: Allow nodedir to be overridden by `NPM_NODEDIR`
- cve-extra-exclusions.inc: add exclusion list for intractable CVE's
- license\_image.bbclass: Detect broken symlinks
- sysstat: make the service start automatically
- sanity: Add error check for '%' in build path
- sanity: Further improve directory sanity tests
- sanity.bbclass: mention `CONNECTIVITY_CHECK_URI` in network failure message
- tzdata: Allow controlling zoneinfo binary format
- oe-time-dd-test.sh: add options and refactor
- vim: add option to disable NLS support
- zstd: Include pzstd in the build
- mirrors.bbclass: provide additional rule for git repo fallbacks
- own-mirrors: Add support for s3:// scheme in `SOURCE_MIRROR_URL`
- common-licenses: add missing SPDX licences
- Add MAINTAINERS.md file to record subsystem maintainers

### Known Issues in 3.4

- Build failures have been reported when running on host Linux systems with FIPS enabled (such as RHEL 8.0 with the FIPS mode enabled). For more details please see [bug #14609](#).

### Recipe Licenses changes in 3.4

The following corrections have been made to the `LICENSE` values set by recipes:

- acpica: correct `LICENSE` to "Intel | BSD-3-Clause | GPLv2"
- dtc: correct `LICENSE` to "GPLv2 | BSD-2-Clause"
- e2fsprogs: correct `LICENSE` to "GPLv2 & LGPLv2 & BSD-3-Clause & MIT"
- ffmpeg: correct `LICENSE` to "GPLv2+ & LGPLv2.1+ & ISC & MIT & BSD-2-Clause & BSD-3-Clause & IJG"
- flac: correct `LICENSE` to "GFDL-1.2 & GPLv2+ & LGPLv2.1+ & BSD-3-Clause"
- flex: correct `LICENSE` to "BSD-3-Clause & LGPL-2.0+"
- font-util: correct `LICENSE` to "MIT & MIT-style & BSD-4-Clause & BSD-2-Clause"
- glib-2.0: correct `LICENSE` to "LGPLv2.1+ & BSD-3-Clause & PD"
- gobject-introspection: correct `LICENSE` to "LGPLv2+ & GPLv2+ & MIT" (add MIT license)
- hdparm: correct `LICENSE` to "BSD-2-Clause & GPLv2 & hdparm"

- `iputils`: correct *LICENSE* to "BSD-3-Clause & GPLv2+"
- `libcap`: correct *LICENSE* to "BSD-3-Clause | GPLv2"
- `libevent`: correct *LICENSE* to "BSD-3-Clause & MIT"
- `libjitterentropy`: correct *LICENSE* to "GPLv2+ | BSD-3-Clause"
- `libpam`: correct *LICENSE* to "GPLv2+ | BSD-3-Clause"
- `libwpe`: correct *LICENSE* to "BSD-2-Clause"
- `libx11-compose-data`: correct *LICENSE* to "MIT & MIT-style & BSD-4-Clause & BSD-2-Clause"
- `libx11`: correct *LICENSE* to "MIT & MIT-style & BSD-4-Clause & BSD-2-Clause"
- `libxfont2`: correct *LICENSE* to "MIT & MIT-style & BSD-4-Clause & BSD-2-Clause"
- `libxfont`: correct *LICENSE* to "MIT & MIT-style & BSD-3-Clause"
- `lsf`: correct *LICENSE* to reflect that it uses a BSD-like (but not exactly BSD) license ("Spencer-94")
- `nfs-utils`: correct *LICENSE* to "MIT & GPLv2+ & BSD-3-Clause"
- `ovmf`: correct license to "BSD-2-Clause-Patent"
- `ppp`: correct *LICENSE* to "BSD-3-Clause & BSD-3-Clause-Attribution & GPLv2+ & LGPLv2+ & PD"
- `python3-packaging`: correct *LICENSE* to "Apache-2.0 | BSD-2-Clause"
- `python-async-test`: correct *LICENSE* to "BSD-3-Clause"
- `quota`: remove BSD license (only BSD licensed part of the code was removed in 4.05)
- `shadow`: correct *LICENSE* to "BSD-3-Clause | Artistic-1.0"
- `shadow-sysroot`: set *LICENSE* the same as shadow
- `sudo`: correct *LICENSE* to "ISC & BSD-3-Clause & BSD-2-Clause & Zlib"
- `swig`: correct *LICENSE* to "BSD-3-Clause & GPLv3"
- `valgrind`: correct license to "GPLv2 & GPLv2+ & BSD-3-Clause"
- `webkitgtk`: correct *LICENSE* to "BSD-2-Clause & LGPLv2+"
- `wpebackend-fdo`: correct *LICENSE* to "BSD-2-Clause"
- `xinetd`: correct *LICENSE* to reflect that it uses a unique BSD-like (but not exactly BSD) license

Other license-related notes:

- When creating recipes for Python software, `recipetool` will now treat "BSD" as "BSD-3-Clause" for the purposes of setting *LICENSE*, as that is the most common understanding.
- Please be aware that an *initramfs* bundled with the kernel using *INITRAMFS\_IMAGE\_BUNDLE* should only contain GPLv2-compatible software; this is now mentioned in the documentation.

## Security Fixes in 3.4

- apr: CVE-2021-35940
- aspell: CVE-2019-25051
- avahi: CVE-2021-3468, CVE-2021-36217
- binutils: CVE-2021-20197
- bluez: CVE-2021-3658
- busybox: CVE-2021-28831
- cairo: CVE-2020-35492
- cpio: CVE-2021-38185
- expat: CVE-2013-0340
- ffmpeg: CVE-2020-20446, CVE-2020-22015, CVE-2020-22021, CVE-2020-22033, CVE-2020-22019, CVE-2021-33815, CVE-2021-38171, CVE-2020-20453
- glibc: CVE-2021-33574, CVE-2021-38604
- inetutils: CVE-2021-40491
- libgcrypt: CVE-2021-40528
- linux-yocto/5.10, 5.14: CVE-2021-3653, CVE-2021-3656
- lz4: CVE-2021-3520
- nettle: CVE-2021-20305
- openssl: CVE-2021-3711, CVE-2021-3712
- perl: CVE-2021-36770
- python3: CVE-2021-29921
- python3-pip: CVE-2021-3572
- qemu: CVE-2020-27821, CVE-2020-29443, CVE-2020-35517, CVE-2021-3392, CVE-2021-3409, CVE-2021-3416, CVE-2021-3527, CVE-2021-3544, CVE-2021-3545, CVE-2021-3546, CVE-2021-3682, CVE-2021-20181, CVE-2021-20221, CVE-2021-20257, CVE-2021-20263
- rpm: CVE-2021-3421, CVE-2021-20271
- rsync: CVE-2020-14387
- util-linux: CVE-2021-37600
- vim: CVE-2021-3770, CVE-2021-3778
- wpa-suplicant: CVE-2021-30004
- xdg-utils: CVE-2020-27748
- xserver-xorg: CVE-2021-3472

## Recipe Upgrades in 3.4

- acl 2.2.53 -> 2.3.1
- acpica 20210105 -> 20210730
- alsa-lib 1.2.4 -> 1.2.5.1
- alsa-plugins 1.2.2 -> 1.2.5
- alsa-tools 1.2.2 -> 1.2.5
- alsa-topology-conf 1.2.4 -> 1.2.5.1
- alsa-ucm-conf 1.2.4 -> 1.2.5.1
- alsa-utils 1.2.4 -> 1.2.5.1
- alsa-utils-scripts 1.2.4 -> 1.2.5.1
- apt 2.2.2 -> 2.2.4
- at 3.2.1 -> 3.2.2
- at-spi2-core 2.38.0 -> 2.40.3
- autoconf-archive 2019.01.06 -> 2021.02.19
- babeltrace2 2.0.3 -> 2.0.4
- bash 5.1 -> 5.1.8
- bind 9.16.16 -> 9.16.20
- binutils 2.36.1 -> 2.37
- binutils-cross 2.36.1 -> 2.37
- binutils-cross-canadian 2.36.1 -> 2.37
- binutils-cross-testsuite 2.36.1 -> 2.37
- binutils-crosssdk 2.36.1 -> 2.37
- bison 3.7.5 -> 3.7.6
- blktrace 1.2.0+gitX -> 1.3.0+gitX
- bluez5 5.56 -> 5.61
- boost 1.75.0 -> 1.77.0
- boost-build-native 4.3.0 -> 4.4.1
- btrfs-tools 5.10.1 -> 5.13.1
- busybox 1.33.1 -> 1.34.0
- busybox-inittab 1.33.0 -> 1.34.0
- ccache 4.2 -> 4.4
- cmake 3.19.5 -> 3.21.1

- cmake-native 3.19.5 -> 3.21.1
- connman 1.39 -> 1.40
- createrepo-c 0.17.0 -> 0.17.4
- cronie 1.5.5 -> 1.5.7
- cross-localedef-native 2.33 -> 2.34
- cups 2.3.3 -> 2.3.3op2
- curl 7.75.0 -> 7.78.0
- dbus-glib 0.110 -> 0.112
- dejagnu 1.6.2 -> 1.6.3
- diffoscope 172 -> 181
- diffutils 3.7 -> 3.8
- distcc 3.3.5 -> 3.4
- dnf 4.6.0 -> 4.8.0
- dpkg 1.20.7.1 -> 1.20.9
- dtc 1.6.0 -> 1.6.1
- e2fsprogs 1.46.1 -> 1.46.4
- elfutils 0.183 -> 0.185
- ell 0.38 -> 0.43
- enchant2 2.2.15 -> 2.3.1
- epiphany 3.38.2 -> 40.3
- ethtool 5.10 -> 5.13
- expat 2.2.10 -> 2.4.1
- ffmpeg 4.3.2 -> 4.4
- file 5.39 -> 5.40
- freetype 2.10.4 -> 2.11.0
- gcc 10.2.0 -> 11.2.0
- gcc-cross 10.2.0 -> 11.2.0
- gcc-cross-canadian 10.2.0 -> 11.2.0
- gcc-crosssdk 10.2.0 -> 11.2.0
- gcc-runtime 10.2.0 -> 11.2.0
- gcc-sanitizers 10.2.0 -> 11.2.0
- gcc-source 10.2.0 -> 11.2.0

- gcr 3.38.1 -> 3.40.0
- gdb 10.1 -> 10.2
- gdb-cross 10.1 -> 10.2
- gdb-cross-canadian 10.1 -> 10.2
- gdk-pixbuf 2.40.0 -> 2.42.6
- ghostscript 9.53.3 -> 9.54.0
- git 2.31.1 -> 2.33.0
- glib-2.0 2.66.7 -> 2.68.4
- glib-networking 2.66.0 -> 2.68.2
- glibc 2.33 -> 2.34
- glibc-locale 2.33 -> 2.34
- glibc-mtrace 2.33 -> 2.34
- glibc-scripts 2.33 -> 2.34
- glibc-testsuite 2.33 -> 2.34
- glslang 11.2.0 -> 11.5.0
- gnome-desktop-testing 2018.1 -> 2021.1
- gnu-config 20210125+gitX -> 20210722+gitX
- gnu-efi 3.0.12 -> 3.0.14
- gnupg 2.2.27 -> 2.3.1
- gobject-introspection 1.66.1 -> 1.68.0
- gpgme 1.15.1 -> 1.16.0
- gptfdisk 1.0.7 -> 1.0.8
- grep 3.6 -> 3.7
- grub 2.04+2.06~rc1 -> 2.06
- grub-efi 2.04+2.06~rc1 -> 2.06
- gsettings-desktop-schemas 3.38.0 -> 40.0
- gtk+3 3.24.25 -> 3.24.30
- harfbuzz 2.7.4 -> 2.9.0
- hdparm 9.60 -> 9.62
- help2man 1.48.2 -> 1.48.4
- hwlatdetect 1.10 -> 2.1
- i2c-tools 4.2 -> 4.3

- icu 68.2 -> 69.1
- igt-gpu-tools 1.25+gitX -> 1.26
- inetutils 2.0 -> 2.1
- iproute2 5.11.0 -> 5.13.0
- iputils s20200821 -> 20210722
- json-glib 1.6.2 -> 1.6.4
- kexec-tools 2.0.21 -> 2.0.22
- kmod 28 -> 29
- kmod-native 28 -> 29
- less 563 -> 590
- libassuan 2.5.4 -> 2.5.5
- libcap 2.48 -> 2.51
- libcgrouper 0.41 -> 2.0
- libcomps 0.1.15 -> 0.1.17
- libconvert-asn1-perl 0.27 -> 0.31
- libdazzle 3.38.0 -> 3.40.0
- libdnf 0.58.0 -> 0.63.1
- libdrm 2.4.104 -> 2.4.107
- libedit 20210216-3.1 -> 20210714-3.1
- libepoxy 1.5.5 -> 1.5.9
- liberation-fonts 2.00.1 -> 2.1.4
- libffi 3.3 -> 3.4.2
- libfm 1.3.1 -> 1.3.2
- libgcc 10.2.0 -> 11.2.0
- libgcc-initial 10.2.0 -> 11.2.0
- libgcrypt 1.9.3 -> 1.9.4
- libgfortran 10.2.0 -> 11.2.0
- libgit2 1.1.0 -> 1.1.1
- libglu 9.0.1 -> 9.0.2
- libgpg-error 1.41 -> 1.42
- libgudev 234 -> 237
- libhandy 1.2.0 -> 1.2.3



- libical 3.0.9 -> 3.0.10
- libidn2 2.3.0 -> 2.3.2
- libinput 1.16.4 -> 1.18.1
- libjitterentropy 3.0.1 -> 3.1.0
- libjpeg-turbo 2.0.6 -> 2.1.1
- libksba 1.5.0 -> 1.6.0
- libmodulemd 2.12.0 -> 2.13.0
- libnsl2 1.3.0 -> 2.0.0
- libnss-mdns 0.14.1 -> 0.15.1
- libogg 1.3.4 -> 1.3.5
- libpcap 1.10.0 -> 1.10.1
- libpcre 8.44 -> 8.45
- libpcre2 10.36 -> 10.37
- libportal 0.3 -> 0.4
- librepo 1.13.0 -> 1.14.1
- libsdl2 2.0.14 -> 2.0.16
- libsolv 0.7.17 -> 0.7.19
- libtasn1 4.16.0 -> 4.17.0
- libtest-needs-perl 0.002006 -> 0.002009
- libtirpc 1.3.1 -> 1.3.2
- libubootenv 0.3.1 -> 0.3.2
- libucontext 0.10+X -> 1.1+X
- liburcu 0.12.2 -> 0.13.0
- libuv 1.41.0 -> 1.42.0
- libva 2.10.0 -> 2.12.0
- libva-initial 2.10.0 -> 2.12.0
- libva-utils 2.10.0 -> 2.12.0
- libwebp 1.2.0 -> 1.2.1
- libwpe 1.8.0 -> 1.10.1
- libx11 1.7.0 -> 1.7.2
- libxcrypt 4.4.18 -> 4.4.25
- libxcrypt-compat 4.4.18 -> 4.4.25

- libxfixes 5.0.3 -> 6.0.0
- libxfont2 2.0.4 -> 2.0.5
- libxft 2.3.3 -> 2.3.4
- libxi 1.7.10 -> 1.7.99.2
- libxkbcommon 1.0.3 -> 1.3.0
- libxml2 2.9.10 -> 2.9.12
- libxres 1.2.0 -> 1.2.1
- linux-libc-headers 5.10 -> 5.14
- linux-yocto 5.4.144+gitX, 5.10.63+gitX -> 5.10.70+gitX, 5.14.9+gitX
- linux-yocto-dev 5.12++gitX -> 5.15++gitX
- linux-yocto-rt 5.4.144+gitX, 5.10.63+gitX -> 5.10.70+gitX, 5.14.9+gitX
- linux-yocto-tiny 5.4.144+gitX, 5.10.63+gitX -> 5.10.70+gitX, 5.14.9+gitX
- llvm 11.1.0 -> 12.0.1
- log4cplus 2.0.6 -> 2.0.7
- logrotate 3.18.0 -> 3.18.1
- ltp 20210121 -> 20210524
- lttnng-modules 2.12.6 -> 2.13.0
- lttnng-tools 2.12.4 -> 2.13.0
- lttnng-ust 2.12.1 -> 2.13.0
- m4 1.4.18 -> 1.4.19
- m4-native 1.4.18 -> 1.4.19
- man-pages 5.10 -> 5.12
- mc 4.8.26 -> 4.8.27
- mesa 21.0.3 -> 21.2.1
- mesa-gl 21.0.3 -> 21.2.1
- meson 0.57.1 -> 0.58.1
- mmc-utils 0.1+gitX (73d6c59af8d1...) -> 0.1+gitX (43282e80e174...)
- mobile-broadband-provider-info 20201225 -> 20210805
- mpg123 1.26.4 -> 1.28.2
- mtd-utils 2.1.2 -> 2.1.3
- mtools 4.0.26 -> 4.0.35
- musl 1.2.2+gitX (e5d2823631bb...) -> 1.2.2+gitX (3f701faace7a...)

- nativesdk-meson 0.57.1 -> 0.58.1
- netbase 6.2 -> 6.3
- nfs-utils 2.5.3 -> 2.5.4
- ofono 1.31 -> 1.32
- openssh 8.5p1 -> 8.7p1
- opkg 0.4.4 -> 0.4.5
- opkg-utils 0.4.3 -> 0.4.5
- ovmf edk2-stable202102 -> edk2-stable202105
- p11-kit 0.23.22 -> 0.24.0
- pango 1.48.2 -> 1.48.9
- patchelf 0.12 -> 0.13
- perl 5.32.1 -> 5.34.0
- piglit 1.0+gitrX (d4d9353b7290...) -> 1.0+gitrX (6a4be9e9946d...)
- pkgconf 1.7.3 -> 1.8.0
- powertop 2.13 -> 2.14
- pseudo 1.9.0+gitX (b988b0a6b8af...) -> 1.9.0+gitX (0cda3ba5f94a...)
- pulseaudio 14.2 -> 15.0
- puzzles 0.0+gitX (84cb4c6701e0...) -> 0.0+gitX (8f3413c31ffd...)
- python3 3.9.5 -> 3.9.6
- python3-attrs 20.3.0 -> 21.2.0
- python3-cython 0.29.22 -> 0.29.24
- python3-dbus 1.2.16 -> 1.2.18
- python3-dbusmock 0.22.0 -> 0.23.1
- python3-docutils 0.16 -> 0.17.1
- python3-git 3.1.14 -> 3.1.20
- python3-gitdb 4.0.5 -> 4.0.7
- python3-hypothesis 6.2.0 -> 6.15.0
- python3-importlib-metadata 3.4.0 -> 4.6.4
- python3-iniparse 0.4 -> 0.5
- python3-jinja2 2.11.3 -> 3.0.1
- python3-libarchive-c 2.9 -> 3.1
- python3-magic 0.4.22 -> 0.4.24

- python3-mako 1.1.4 -> 1.1.5
- python3-markupsafe 1.1.1 -> 2.0.1
- python3-more-itertools 8.7.0 -> 8.8.0
- python3-numpy 1.20.1 -> 1.21.2
- python3-packaging 20.9 -> 21.0
- python3-pathlib2 2.3.5 -> 2.3.6
- python3-pbr 5.4.4 -> 5.6.0
- python3-pip 20.0.2 -> 21.2.4
- python3-pluggy 0.13.1 -> 1.0.0
- python3-pycairo 1.20.0 -> 1.20.1
- python3-pygments 2.8.1 -> 2.10.0
- python3-pyobject 3.38.0 -> 3.40.1
- python3-pytest 6.2.2 -> 6.2.4
- python3-scons 3.1.2 -> 4.2.0
- python3-scons-native 3.1.2 -> 4.2.0
- python3-setuptools 54.1.1 -> 57.4.0
- python3-setuptools-scm 5.0.1 -> 6.0.1
- python3-six 1.15.0 -> 1.16.0
- python3-sortedcontainers 2.3.0 -> 2.4.0
- python3-testtools 2.4.0 -> 2.5.0
- python3-zipp 3.4.1 -> 3.5.0
- qemu 5.2.0 -> 6.0.0
- qemu-native 5.2.0 -> 6.0.0
- qemu-system-native 5.2.0 -> 6.0.0
- re2c 2.0.3 -> 2.2
- rng-tools 6.11 -> 6.14
- rpcbind 1.2.5 -> 1.2.6
- rt-tests 1.10 -> 2.1
- ruby 3.0.1 -> 3.0.2
- rxvt-unicode 9.22 -> 9.26
- shaderc 2020.5 -> 2021.1
- shadow 4.8.1 -> 4.9

- spirv-tools 2020.7 -> 2021.2
- sqlite3 3.35.0 -> 3.36.0
- squashfs-tools 4.4 -> 4.5
- strace 5.11 -> 5.14
- stress-ng 0.12.05 -> 0.13.00
- sudo 1.9.6p1 -> 1.9.7p2
- swig 3.0.12 -> 4.0.2
- sysklogd 2.2.2 -> 2.2.3
- systemd 247.6 -> 249.3
- systemd-boot 247.6 -> 249.3
- systemd-conf 247.6 -> 1.0
- systemtap 4.4 -> 4.5
- systemtap-native 4.4 -> 4.5
- systemtap-uprobes 4.4 -> 4.5
- tcf-agent 1.7.0+gitX (a022ef2f1acf...) -> 1.7.0+gitX (2735e3d6b7ec...)
- texinfo 6.7 -> 6.8
- tiff 4.2.0 -> 4.3.0
- u-boot 2021.01 -> 2021.07
- u-boot-tools 2021.01 -> 2021.07
- usbutils 013 -> 014
- util-linux 2.36.2 -> 2.37.2
- util-linux-libuuid 2.36.2 -> 2.37.2
- vala 0.50.4 -> 0.52.5
- valgrind 3.16.1 -> 3.17.0
- virglrenderer 0.8.2 -> 0.9.1
- vte 0.62.2 -> 0.64.2
- vulkan-headers 1.2.170.0 -> 1.2.182.0
- vulkan-loader 1.2.170.0 -> 1.2.182.0
- vulkan-samples git (55cebd9e7cc4...) -> git (d2187278cb66...)
- vulkan-tools 1.2.170.0 -> 1.2.182.0
- wayland-protocols 1.20 -> 1.21
- webkitgtk 2.30.5 -> 2.32.3

- wireless-regdb 2021.04.21 -> 2021.07.14
- wpebackend-fdo 1.8.0 -> 1.10.0
- x264 r3039+gitX (544c61f08219...) -> r3039+gitX (5db6aa6cab1b...)
- xeyes 1.1.2 -> 1.2.0
- xf86-input-libinput 0.30.0 -> 1.1.0
- xkbcomp 1.4.4 -> 1.4.5
- xkeyboard-config 2.32 -> 2.33
- xorgproto 2020.1 -> 2021.4.99.2
- xserver-xorg 1.20.10 -> 1.20.13
- zstd 1.4.9 -> 1.5.0

### **Contributors to 3.4**

Thanks to the following people who contributed to this release:

- Adam Romanek
- Alejandro Hernandez Samaniego
- Alexander Kanavin
- Alexandre Belloni
- Alexey Brodtkin
- Alex Stewart
- Alistair Francis
- Anatol Belski
- Anders Wallin
- Andrea Adami
- Andreas Müller
- Andrej Valek
- Andres Beltran
- Andrey Zhizhikin
- Anibal Limon
- Anthony Bagwell
- Anton Blanchard
- Anuj Mittal
- Armin Kuster
- Asfak Rahman

- Bastian Krause
- Bernhard Rosenkränzer
- Bruce Ashfield
- Carlos Rafael Giani
- Chandana kalluri
- Changhyeok Bae
- Changqing Li
- Chanho Park
- Chen Qi
- Chris Laplante
- Christophe Chapuis
- Christoph Muellner
- Claudius Heine
- Damian Wrobel
- Daniel Ammann
- Daniel Gomez
- Daniel McGregor
- Daniel Wagenknecht
- Denys Dmytriienko
- Devendra Tewari
- Diego Sueiro
- Dmitry Baryshkov
- Douglas Royds
- Dragos-Marian Panait
- Drew Moseley
- Enrico Scholz
- Fabio Berton
- Florian Amstutz
- Gavin Li
- Guillaume Champagne
- Harald Brinkmann
- Henning Schild

- He Zhe
- Hongxu Jia
- Hsia-Jun (Randy) Li
- Jean Bouchard
- Joe Slater
- Jonas Höppner
- Jon Mason
- Jose Quaresma
- Joshua Watt
- Justin Bronder
- Kai Kang
- Kenfe-Mickael Laventure
- Kevin Hao
- Khairul Rohaizzat Jamaluddin
- Khem Raj
- Kiran Surendran
- Konrad Weihmann
- Kristian Klausen
- Kyle Russell
- Lee Chee Yang
- Lei Maohui
- Luca Boccassi
- Marco Felsch
- Marcus Comstedt
- Marek Vasut
- Mark Hatle
- Markus Volk
- Marta Rybczynska
- Martin Jansa
- Matthias Klein
- Matthias Schiffer
- Matt Madison



- Matt Spencer
- Max Krummenacher
- Michael Halstead
- Michael Ho
- Michael Opdenacker
- Mike Crowe
- Mikko Rapeli
- Ming Liu
- Mingli Yu
- Minjae Kim
- Nicolas Dechesne
- Niels Avonds
- Nikolay Papenkov
- Nisha Parrakat
- Olaf Mandel
- Oleksandr Kravchuk
- Oleksandr Popovych
- Oliver Kranz
- Otavio Salvador
- Patrick Williams
- Paul Barker
- Paul Eggleton
- Paul Gortmaker
- Paulo Cesar Zaneti
- Peter Bergin
- Peter Budny
- Peter Kjellerstedt
- Petr Vorel
- Przemyslaw Gorszkowski
- Purushottam Choudhary
- Qiang Zhang
- Quentin Schulz

- Ralph Siemsen
- Randy MacLeod
- Ranjitsinh Rathod
- Rasmus Villemoes
- Reto Schneider
- Richard Purdie
- Richard Weinberger
- Robert Joslyn
- Robert P. J. Day
- Robert Yang
- Romain Naour
- Ross Burton
- Sakib Sajal
- Samuli Piippo
- Saul Wold
- Scott Murray
- Scott Weaver
- Stefan Ghinea
- Stefan Herbrechtsmeier
- Stefano Babic
- Stefan Wiehler
- Steve Sakoman
- Teoh Jay Shen
- Thomas Perrot
- Tim Orling
- Tom Pollard
- Tom Rini
- Tony Battersby
- Tony Tascioglou
- Trevor Gamblin
- Trevor Woerner
- Ulrich Ölmann

- Valentin Danaila
- Vinay Kumar
- Vineela Tummalapalli
- Vinicius Ossanes Aquino
- Vivien Didelot
- Vyacheslav Yurkov
- Wang Mingyu
- Wes Lindauer
- William A. Kennington III
- Yanfei Xu
- Yann Dirson
- Yi Fan Yu
- Yi Zhao
- Zang Ruochen
- Zheng Ruoqin
- Zoltan Boszormenyi

## Repositories / Downloads for 3.4

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `honister`
- Tag: `yocto-3.4`
- Git Revision: `f6d1126fff213460dc6954a5d5fc168606d76b66`
- Release Artefact: `poky-f6d1126fff213460dc6954a5d5fc168606d76b66`
- sha: `11e8f5760f704eed1ac37a5b09b1a831b5254d66459be75b06a72128c63e0411`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4/poky-f6d1126fff213460dc6954a5d5fc168606d76b66.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto/yocto-3.4/poky-f6d1126fff213460dc6954a5d5fc168606d76b66.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `honister`
- Tag: `2021-10-honister`
- Git Revision: `bb1dea6806f084364b6017db2567f438e805aef0`
- Release Artefact: `oecore-bb1dea6806f084364b6017db2567f438e805aef0`

- sha: 9a356c407c567b1c26e535cad235204b0462cb79321fefb0844324a6020b31f4
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4/oecore-bb1dea6806f084364b6017db2567f438e805aef0.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4/oecore-bb1dea6806f084364b6017db2567f438e805aef0.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: honister
- Tag: yocto-3.4
- Git Revision: f5d761cbd5c957e4405c5d40b0c236d263c916a8
- Release Artefact: meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8
- sha: d4305d638ef80948584526c8ca386a8cf77933dff8a3b8da98d26a5c40fcc11
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>

#### meta-intel

- Repository Location: <https://git.yoctoproject.org/meta-intel>
- Branch: honister
- Tag: yocto-3.4
- Git Revision: 90170cf85fe35b4e8dc00eee50053c0205276b63
- Release Artefact: meta-intel-90170cf85fe35b4e8dc00eee50053c0205276b63
- sha: 2b3b43386dfcaaa880d819c1ae88b1251b55fb12c622af3d0936c3dc338491fc
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4/meta-intel-90170cf85fe35b4e8dc00eee50053c0205276b63.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4/meta-intel-90170cf85fe35b4e8dc00eee50053c0205276b63.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: honister
- Tag: yocto-3.4
- Git Revision: f04e4369bf9dd3385165281b9fa2ed1043b0e400
- Release Artefact: meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400
- sha: ef8e2b1ec1fb43dbec4ff6990ac736315c7bc2d8c8e79249e1d337558657d3fe
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 1.52
- Tag: 2021-10-honister
- Git Revision: [c78ebac71ec976fdf27ea24767057882870f5c60](#)
- Release Artefact: [bitbake-c78ebac71ec976fdf27ea24767057882870f5c60](#)
- sha: [8077c7e7528cd73ef488ef74de3943ec66cae361459e5b630fb3cbe89c498d3d](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4/bitbake-c78ebac71ec976fdf27ea24767057882870f5c60.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto/yocto-3.4/bitbake-c78ebac71ec976fdf27ea24767057882870f5c60.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: honister
- Tag: yocto-3.4
- Git Revision: [d75c5450ecf56c8ac799a633ee9ac459e88f91fc](#)

### 17.12.3 Release notes for 3.4.1 (honister)

#### Known Issues in 3.4.1

- [bsps-hw.bsps-hw.Test\\_Seek\\_bar\\_and\\_volume\\_control](#) manual test case failure

#### Security Fixes in 3.4.1

- glibc: Backport fix for [CVE-2021-43396](#)
- vim: add patch number to [CVE-2021-3778](#) patch
- vim: fix [CVE-2021-3796](#), [CVE-2021-3872](#), and [CVE-2021-3875](#)
- squashfs-tools: follow-up fix for [CVE-2021-41072](#)
- avahi: update CVE id fixed by [local-ping.patch](#)
- squashfs-tools: fix [CVE-2021-41072](#)
- ffmpeg: fix [CVE-2021-38114](#)
- curl: fix [CVE-2021-22945](#), [CVE-2021-22946](#) and [CVE-2021-22947](#)

#### Fixes in 3.4.1

- bitbake.conf: Fix corruption of GNOME mirror url
- bitbake.conf: Use wayland distro feature for native builds
- bitbake: Revert "parse/ast: Show errors for append/prepend/remove operators combined with +=/./="
- bitbake: bitbake-worker: Add debug when unpickle fails
- bitbake: cooker: Fix task-depends.dot for multiconfig targets

- bitbake: cooker: Handle parse threads disappearing to avoid hangs
- bitbake: cooker: Handle parsing results queue race
- bitbake: cooker: Remove debug code, oops :(
- bitbake: cooker: check if upstream hash equivalence server is available
- bitbake: fetch/git: Handle github dropping git:// support
- bitbake: fetch/wget: Add timeout for checkstatus calls (30s)
- bitbake: fetch2/perforce: Fix typo
- bitbake: fetch2: Fix url remap issue and add testcase
- bitbake: fetch2: fix downloadfilename issue with premirror
- bitbake: fetch: Handle mirror user/password replacements correctly
- bitbake: parse/ast: Show errors for append/prepend/remove operators combined with +=/=
- bitbake: runqueue: Fix runall option handling
- bitbake: runqueue: Fix runall option task deletion ordering issue
- bitbake: test/fetch: Update urls to match upstream branch name changes
- bitbake: tests/fetch.py: add test case to ensure downloadfilename is used for premirror
- bitbake: tests/fetch.py: fix premirror test cases
- bitbake: tests/fetch: Update github urls
- bitbake: tests/fetch: Update pcre.org address after github changes
- bitbake: tests/runqueue: Ensure hashserv exits before deleting files
- bitbake: utils: Handle lockfile filenames that are too long for filesystems
- bootchart2: Don't compile Python modules
- build-appliance-image: Update to honister head revision
- buildhistory: Fix package output files for SDKs
- busybox: 1.34.0 -> 1.34.1
- ca-certificates: update 20210119 -> 20211016
- classes/populate\_sdk\_base: Add setscene tasks
- conf: update for release 3.4
- convert-srcuri.py: use regex to check space in *SRC\_URI*
- create-spdx: Fix key errors in do\_create\_runtime\_spdx
- create-spdx: Protect against None from *LICENSE\_PATH*
- create-spdx: Set the Organization field via a variable
- create-spdx: add create\_annotation function

- create-spdx: cross recipes are native also
- create\_spdx: ensure is\_work\_shared() is unique
- cups: Fix missing installation of cups sysv init scripts
- docs: poky.yaml: updates for 3.4
- dpkg: Install dkpg-perl scripts to versioned perl directory
- glibc-version.inc: remove branch= from GLIBC\_GIT\_URI
- go-helloworld/glide: Fix urls
- go.bbclass: Allow adding parameters to go ldflags
- go: upgrade 1.16.7 -> 1.16.8
- gst-devtools: 1.18.4 -> 1.18.5
- gst-examples: 1.18.4 -> 1.18.5
- gstreamer1.0-libav: 1.18.4 -> 1.18.5
- gstreamer1.0-omx: 1.18.4 -> 1.18.5
- gstreamer1.0-plugins-bad: 1.18.4 -> 1.18.5
- gstreamer1.0-plugins-base: 1.18.4 -> 1.18.5
- gstreamer1.0-plugins-good: 1.18.4 -> 1.18.5
- gstreamer1.0-plugins-ugly: 1.18.4 -> 1.18.5
- gstreamer1.0-python: 1.18.4 -> 1.18.5
- gstreamer1.0-rtsp-server: 1.18.4 -> 1.18.5
- gstreamer1.0-vaapi: 1.18.4 -> 1.18.5
- gstreamer1.0: 1.18.4 -> 1.18.5
- insane.bbclass: Add a check for directories that are expected to be empty
- kernel-devsrc: Add vdso.lds and other build files for riscv64 as well
- libnewt: Use python3targetconfig to fix reproducibility issue
- libpcr/libpcr2: correct *SRC\_URI*
- libx11-compose-data: Update *LICENSE* to better reflect reality
- libx11: Update *LICENSE* to better reflect reality
- libxml2: Use python3targetconfig to fix reproducibility issue
- linunistring: Add missing gperf-native dependency
- linux-firmware: upgrade to 20211027
- linux-yocto-dev: Ensure *DEPENDS* matches recent 5.14 kernel changes
- linux-yocto-rt/5.10: update to -rt54

- linux-yocto/5.10: update to v5.10.78
- linux-yocto/5.14: common-pc: enable CONFIG\_ATA\_PIIX as built-in
- linux-yocto/5.14: update to v5.14.17
- linux-yocto: add libmpc-native to *DEPENDS*
- ltngng-tools: replace ad hoc ptest fixup with upstream fixes
- manuals: releases.rst: move gatesgarth to outdated releases section
- mesa: Enable svga for x86 only
- mesa: upgrade 21.2.1 -> 21.2.4
- meson.bbclass: Remove empty egg-info directories before running meson
- meson: install native file in sdk
- meson: move lang args to the right section
- meson: set objcopy in the cross and native toolchain files
- meta/scripts: Manual git url branch additions
- meta: Add explicit branch to git SRC\_URIs
- migration-3.4: add additional migration info
- migration-3.4: add some extra packaging notes
- migration-3.4: tweak overrides change section
- migration: tweak introduction section
- mirrors: Add kernel.org sources mirror for downloads.yoctoproject.org
- mirrors: Add uninative mirror on kernel.org
- nativesdk-packagegroup-sdk-host.bb: Update host tools for wayland
- oeqa/runtime/parselogs: modified drm error in common errors list
- oeqa/selftest/sstatetests: fix typo ware -> were
- oeqa: Update cleanup code to wait for hashserv exit
- opkg: Fix poor operator combination choice
- ovmf: update 202105 -> 202108
- patch.bbclass: when the patch fails show more info on the fatal error
- poky.conf: bump version for 3.4.1 honister release
- poky.yaml: add lz4 and zstd to essential host packages
- poky.yaml: fix lz4 package name for older Ubuntu versions
- pseudo: Add fcntl64 wrapper
- python3-setuptools: \_distutils/sysconfig fix



- python3: update to 3.9.7
- qemu.inc: Remove empty egg-info directories before running meson
- recipes: Update github.com urls to use https
- ref-manual: Update how to set a useradd password
- ref-manual: document "reproducible\_build" class and *SOURCE\_DATE\_EPOCH*
- ref-manual: document BUILD\_REPRODUCIBLE\_BINARIES
- ref-manual: document *TOOLCHAIN\_HOST\_TASK\_ESDK*
- ref-manual: remove meta class
- ref-manual: update system requirements
- releases.rst: fix release number for 3.3.3
- scripts/convert-srcuri: Update *SRC\_URI* conversion script to handle github url changes
- scripts/lib/wic/help.py: Update Fedora Kickstart URLs
- scripts/oe-package-browser: Fix after overrides change
- scripts/oe-package-browser: Handle no packages being built
- spdx.py: Add annotation to relationship
- sstate: Account for reserved characters when shortening sstate filenames
- sstate: another fix for touching files inside pseudo
- sstate: fix touching files inside pseudo
- staging: Fix autoconf-native rebuild failure
- strace: fix build against 5.15 kernel/kernel-headers
- strace: show test suite log on failure
- stress-ng: convert to git, website is down
- systemd: add missing include for musl
- tar: filter CVEs using vendor name
- test-manual: how to enable reproducible builds
- testimage: fix unclosed testdata file
- tzdata: update 2021d to 2021d
- uninative: Add version to uninative tarball name
- waffle: convert to git, website is down
- wayland: Fix wayland-tools packaging
- wireless-regdb: upgrade 2021.07.14 -> 2021.08.28
- wpa-suplicant: Match package override to *PACKAGES* for pkg\_postinst

### Contributors to 3.4.1

- Ahmed Hossam
- Alexander Kanavin
- Alexandre Belloni
- Andrej Valek
- Andres Beltran
- Anuj Mittal
- Bruce Ashfield
- Chen Qi
- Claus Stovgaard
- Daiane Angolini
- Hsia-Jun(Randy) Li
- Jon Mason
- Jose Quaresma
- Joshua Watt
- Kai Kang
- Khem Raj
- Kiran Surendran
- Manuel Leonhardt
- Michael Opdenacker
- Oleksandr Kravchuk
- Pablo Saavedra
- Paul Eggleton
- Peter Kjellerstedt
- Quentin Schulz
- Ralph Siemsen
- Randy Li
- Richard Purdie
- Ross Burton
- Sakib Sajal
- Saul Wold
- Teoh Jay Shen

- Tim Orling
- Tom Hochstein
- Yureka

## Repositories / Downloads for 3.4.1

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `honister`
- Tag: `yocto-3.4.1`
- Git Revision: `b53230c08d9f02ecaf35b4f0b70512abbf10ae11`
- Release Artefact: `poky-b53230c08d9f02ecaf35b4f0b70512abbf10ae11`
- sha: `57d49e2afafb555baf65643acf752464f0eb7842b964713a5de7530c392de159`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.1/poky-b53230c08d9f02ecaf35b4f0b70512abbf10ae11.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto-3.4.1/poky-b53230c08d9f02ecaf35b4f0b70512abbf10ae11.tar.bz2>

### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `honister`
- Tag: `yocto-3.4.1`
- Git Revision: `f5d761cbd5c957e4405c5d40b0c236d263c916a8`
- Release Artefact: `meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8`
- sha: `d4305d638ef80948584526c8ca386a8cf77933dff8a3b8da98d26a5c40fcc11`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.1/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>, [http://mirrors.kernel.org/yocto/yocto-3.4.1/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2](http://mirrors.kernel.org/yocto/yocto/yocto-3.4.1/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2)

### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `honister`
- Tag: `yocto-3.4.1`
- Git Revision: `f04e4369bf9dd3385165281b9fa2ed1043b0e400`
- Release Artefact: `meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400`
- sha: `ef8e2b1ec1fb43dbee4ff6990ac736315c7bc2d8c8e79249e1d337558657d3fe`
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>, [http://mirrors.kernel.org/yocto/yocto-3.4/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2](http://mirrors.kernel.org/yocto/yocto/yocto-3.4/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2)

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 1.52
- Tag: yocto-3.4.1
- Git Revision: 44a83b373e1fc34c93cd4a6c6cf8b73b230c1520
- Release Artefact: bitbake-44a83b373e1fc34c93cd4a6c6cf8b73b230c1520
- sha: 03d50c1318d88d62eb01d359412ea5a8014ef506266629a2bd43ab3a2ef19430
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.1/bitbake-44a83b373e1fc34c93cd4a6c6cf8b73b230c1520.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.1/bitbake-44a83b373e1fc34c93cd4a6c6cf8b73b230c1520.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: honister
- Tag: yocto-3.4.1
- Git Revision: b250eda5a0beba8acc9641c55a5b0e30594b5178

### 17.12.4 Release notes for 3.4.2 (honister)

#### Security Fixes in 3.4.2

- tiff: backport fix for CVE-2022-22844
- glibc : Fix CVE-2021-3999
- glibc : Fix CVE-2021-3998
- glibc : Fix CVE-2022-23219
- glibc : Fix CVE-2022-23218
- lighttpd: backport a fix for CVE-2022-22707
- speex: fix CVE-2020-23903
- linux-yocto/5.10: amdgpu: updates for CVE-2021-42327
- libsndfile1: fix CVE-2021-4156
- xserver-xorg: whitelist two CVEs
- grub2: fix CVE-2021-3981
- xserver-xorg: update *CVE\_PRODUCT*
- binutils: CVE-2021-42574
- gcc: Fix CVE-2021-42574
- gcc: Fix CVE-2021-35465

- cve-extra-exclusions: add db CVEs to exclusion list
- gcc: Add [CVE-2021-37322](#) to the list of CVEs to ignore
- bind: fix [CVE-2021-25219](#)
- openssh: fix [CVE-2021-41617](#)
- ncurses: fix [CVE-2021-39537](#)
- vim: fix [CVE-2021-3968](#) and [CVE-2021-3973](#)
- vim: fix [CVE-2021-3927](#) and [CVE-2021-3928](#)
- gmp: fix [CVE-2021-43618](#)

### Fixes in 3.4.2

- build-appliance-image: Update to honister head revision
- poky.conf: bump version for 3.4.2 release
- libxml2: Backport python3-lxml workaround patch
- core-image-sato-sdk: allocate more memory when in qemu
- vim: upgrade to patch 4269
- vim: update to include latest CVE fixes
- expat: upgrade to 2.4.4
- libusb1: correct [SRC\\_URI](#)
- yocto-check-layer: add debug output for the layers that were found
- linux-firmware: Add CLM blob to linux-firmware-bcm4373 package
- linux-yocto/5.10: update to v5.10.93
- icu: fix make\_icudata dependencies
- sstate: Improve failure to obtain archive message/handling
- insane.bbclass: Correct package\_qa\_check\_empty\_dirs()
- sstate: A third fix for touching files inside pseudo
- kernel: introduce python3-dtschema-wrapper
- vim: upgrade to 8.2 patch 3752
- bootchart2: Add missing python3-math dependency
- socat: update [SRC\\_URI](#)
- pigz: fix one failure of command "unpigz -l"
- linux-yocto/5.14: update genericx86\* machines to v5.14.21
- linux-yocto/5.10: update genericx86\* machines to v5.10.87
- go: upgrade 1.16.10 -> 1.16.13

- linux-yocto/5.10/cfg: add kcov feature fragment
- linux-yocto/5.14: fix arm 32bit -rt warnings
- oeqa/sstate: Fix allarch samesigs test
- rootfs-postcommands.bbclass: Make two comments use the new variable syntax
- cve-check: add lockfile to task
- lib/oe/reproducible: correctly set .git location when recursively looking for git repos
- epiphany: Update 40.3 -> 40.6
- scripts/buildhistory-diff: drop use of distutils
- scripts: Update to use exec\_module() instead of load\_module()
- vulkan-loader: inherit pkgconfig
- webkitgtk: Add reproducibility fix
- openssl: Add reproducibility fix
- rpm: remove tmp folder created during install
- package\_manager: ipk: Fix host manifest generation
- bitbake: utils: Update to use exec\_module() instead of load\_module()
- linux-yocto: add libmpc-native to *DEPENDS*
- ref-manual: fix patch documentation
- bitbake: tests/fetch: Drop gnu urls from wget connectivity test
- bitbake: fetch: npm: Use temporary file for empty user config
- bitbake: fetch: npm: Quote destdir in run chmod command
- bitbake: process: Do not mix stderr with stdout
- xserver-xorg: upgrade 1.20.13 -> 1.20.14
- python3-pyelftools: Depend on debugger, pprint
- linux-firmware: upgrade 20211027 -> 20211216
- oeqa/selftest/bbtests: Use YP sources mirror instead of GNU
- systemd: Fix systemd-journal-gateway user/groups
- license.bbclass: implement ast.NodeVisitor.visit\_Constant
- oe/license: implement ast.NodeVisitor.visit\_Constant
- packagedata.py: silence a DeprecationWarning
- uboot-sign: fix the concatenation when multiple U-BOOT configurations are specified
- runqemu: check the qemu PID has been set before kill()ing it
- selftest/devtool: Check branch in git fetch

- recipetool: Set master branch only as fallback
- kern-tools: bug fixes and kgit-gconfig
- linux-yocto-rt/5.10: update to -rt56
- linux-yocto/5.14: update to v5.14.21
- python3: upgrade 3.9.7 -> 3.9.9
- bitbake: lib/pyinotify.py: Remove deprecated module asyncore
- updates for recent releases
- libdrm: upgrade 2.4.108 -> 2.4.109
- patch.py: Initialize git repo before patching
- boost: Fix build on arches with no atomics
- boost: allow searching for python310
- recipetool: extend curl detection when creating recipes
- recipetool: handle GitLab URLs like we do GitHub
- README.OE-Core.md: update URLs
- libtool: change the default AR\_FLAGS from "cru" to "cr"
- libtool: Update patchset to match those submitted upstream
- scripts/checklayer/common.py: Fixed a minor grammatical error
- oeqa/parselogs: Fix quoting
- oeqa/utis/dump: Fix typo
- systemd: update 249.6 -> 249.7
- glibc: Fix i586/c3 support
- wic: support rootdev identified by partition label
- buildhistory: Fix screvs output
- classes/crate-fetch: Ensure crate fetcher is available
- rootfs-postcommands: update systemd\_create\_users
- classes/meson: Add optional rust definitions
- rust-cross: Replace *TARGET\_ARCH* with *TUNE\_PKGARCH*
- maintainers.inc: fix up rust-cross entry
- rust-cross: Fix directory not deleted for race glibc vs. musl
- wic: use shutil.which
- bitbake: data\_smart.py: Skip old override syntax checking for anonymous functions
- documentation: conf.py: fix version of bitbake objects.inv

- updates for release 3.3.4

### **Contributors to 3.4.2**

- Alexander Kanavin
- Alexandre Belloni
- Anton Mikanovich
- Anuj Mittal
- Bruce Ashfield
- Carlos Rafael Giani
- Chaitanya Vadrevu
- Changqing Li
- Dhruva Gole
- Florian Amstutz
- Joshua Watt
- Kai Kang
- Khairul Rohaizzat Jamaluddin
- Khem Raj
- Konrad Weihmann
- Kory Maincent
- Li Wang
- Marek Vasut
- Markus Volk
- Martin Jansa
- Max Krummenacher
- Michael Opdenacker
- Mingli Yu
- Oleksiy Obitotskyy
- Pavel Zhukov
- Peter Kjellerstedt
- Pgowda
- Quentin Schulz
- Richard Purdie
- Robert Yang



- Ross Burton
- Rudolf J Streif
- Sakib Sajal
- Samuli Piippo
- Schmidt, Adriaan
- Stefan Herbrechtsmeier
- Steve Sakoman
- Sundeep KOKKONDA
- Teoh Jay Shen
- Thomas Perrot
- Tim Orling
- Vyacheslav Yurkov
- Yongxin Liu
- pgowda
- Wang Mingyu

## Repositories / Downloads for 3.4.2

### poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [honister](#)
- Tag: [yocto-3.4.2](#)
- Git Revision: [e0ab08bb6a32916b457d221021e7f402ffa36b1a](#)
- Release Artefact: [poky-e0ab08bb6a32916b457d221021e7f402ffa36b1a](#)
- sha: [8580dc5067ee426fe347a0d0f7a74c29ba539120bbe8438332339a9c8bce00fd](#)
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.2/poky-e0ab08bb6a32916b457d221021e7f402ffa36b1a.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.2/poky-e0ab08bb6a32916b457d221021e7f402ffa36b1a.tar.bz2>

### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: [honister](#)
- Tag: [yocto-3.4.2](#)
- Git Revision: [418a9c4c31615a9e3e011fc2b21fb7154bc6c93a](#)
- Release Artefact: [oecore-418a9c4c31615a9e3e011fc2b21fb7154bc6c93a](#)
- sha: [f2ca94a5a7ec669d4c208d1729930dfc1b917846dbb2393d01d6d5856fcbc6de](#)

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.2/oecore-418a9c4c31615a9e3e011fc2b21fb7154bc6c93a.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.2/oecore-418a9c4c31615a9e3e011fc2b21fb7154bc6c93a.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: honister
- Tag: yocto-3.4.2
- Git Revision: f5d761cbd5c957e4405c5d40b0c236d263c916a8
- Release Artefact: meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8
- sha: d4305d638ef80948584526c8ca386a8cf77933dff8a3b8da98d26a5c40fcc11
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.2/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.2/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: honister
- Tag: yocto-3.4.2
- Git Revision: f04e4369bf9dd3385165281b9fa2ed1043b0e400
- Release Artefact: meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400
- sha: ef8e2b1ec1fb43dbec4ff6990ac736315c7bc2d8c8e79249e1d337558657d3fe
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.2/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.2/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>
- Branch: 1.52
- Tag: yocto-3.4.2
- Git Revision: c039182c79e2ccc54fff5d7f4f266340014ca6e0
- Release Artefact: bitbake-c039182c79e2ccc54fff5d7f4f266340014ca6e0
- sha: bd80297f8d8aa40cbcc8a3d4e23a5223454b305350adf34cd29b5fb65c1b4c52
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.2/bitbake-c039182c79e2ccc54fff5d7f4f266340014ca6e0.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.2/bitbake-c039182c79e2ccc54fff5d7f4f266340014ca6e0.tar.bz2>

#### yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>

- Branch: [honister](#)
- Tag: [yocto-3.4.2](#)
- Git Revision: [3061d3d62054a5c3b9e16bfce4bcd186fa7a23d2](#)

## 17.12.5 Release notes for 3.4.3 (honister)

### Security Fixes in 3.4.3

- ghostscript: fix [CVE-2021-3781](#)
- ghostscript: fix [CVE-2021-45949](#)
- tiff: Add backports for two CVEs from upstream ([CVE-2022-0561](#) & [CVE-2022-0562](#))
- gcc : Fix [CVE-2021-46195](#)
- virglrenderer: fix [CVE-2022-0135](#) and [CVE-2022-0175](#)
- binutils: Add fix for [CVE-2021-45078](#)

### Fixes in 3.4.3

- Revert "cve-check: add lockfile to task"
- asciidoc: update git repository
- bitbake: build: Tweak exception handling for setscene tasks
- bitbake: contrib: Fix hash server Dockerfile dependencies
- bitbake: cooker: Improve parsing failure from handled exception usability
- bitbake: data\_smart: Fix overrides file/line message additions
- bitbake: fetch2: ssh: username and password are optional
- bitbake: tests/fetch: Handle upstream master -> main branch change
- bitbake: utils: Ensure shell function failure in python logging is correct
- build-appliance-image: Update to honister head revision
- build-appliance-image: Update to honister head revision
- coreutils: remove obsolete ignored CVE list
- crate-fetch: fix setscene failures
- cups: Add --with-dbusdir to [EXTRA\\_OECONF](#) for deterministic build
- cve-check: create directory of CVE\_CHECK\_MANIFEST before copy
- cve-check: get\_cve\_info should open the database read-only
- default-distrovars.inc: Switch connectivity check to a yoctoproject.org page
- depmodwrapper-cross: add config directory option
- devtool: deploy-target: Remove stripped binaries in pseudo context

- devtool: explicitly set main or master branches in upgrades when available
- docs: fix hardcoded link warning messages
- documentation: conf.py: update for 3.4.2
- documentation: prepare for 3.4.3 release
- expat: Upgrade to 2.4.7
- gcc-target: fix glob to remove gcc-<version> binary
- gcsections: add nativesdk-cairo to exclude list
- go: update to 1.16.15
- gst-devtools: 1.18.5 -> 1.18.6
- gst-examples: 1.18.5 -> 1.18.6
- gstreamer1.0-libav: 1.18.5 -> 1.18.6
- gstreamer1.0-omx: 1.18.5 -> 1.18.6
- gstreamer1.0-plugins-bad: 1.18.5 -> 1.18.6
- gstreamer1.0-plugins-base: 1.18.5 -> 1.18.6
- gstreamer1.0-plugins-good: 1.18.5 -> 1.18.6
- gstreamer1.0-plugins-ugly: 1.18.5 -> 1.18.6
- gstreamer1.0-python: 1.18.5 -> 1.18.6
- gstreamer1.0-rtsp-server: 1.18.5 -> 1.18.6
- gstreamer1.0-vaapi: 1.18.5 -> 1.18.6
- gstreamer1.0: 1.18.5 -> 1.18.6
- harfbuzz: upgrade 2.9.0 -> 2.9.1
- initramfs-framework: unmount automounts before switch\_root
- kernel-devsrc: do not copy Module.symvers file during install
- libarchive : update to 3.5.3
- libpcap: Disable DPDK explicitly
- libxml-parser-perl: Add missing *RDEPENDS*
- linux-firmware: upgrade 20211216 -> 20220209
- linux-yocto/5.10: Fix ramoops/ftrace
- linux-yocto/5.10: features/zram: remove CONFIG\_ZRAM\_DEF\_COMP
- linux-yocto/5.10: fix dssall build error with binutils 2.3.8
- linux-yocto/5.10: ppc/riscv: fix build with binutils 2.3.8
- linux-yocto/5.10: update genericx86\* machines to v5.10.99

- linux-yocto/5.10: update to v5.10.103
- mc: fix build if ncurses have been configured without wide characters
- oeqa/buildtools: Switch to our webserver instead of example.com
- patch.py: Prevent git repo reinitialization
- perl: Improve and update module RPDEPENDS
- poky.conf: bump version for 3.4.3 honister release
- qemuboot: Fix build error if UNINATIVE\_LOADER is unset
- quilt: Disable external sendmail for deterministic build
- recipetool: Fix circular reference in *SRC\_URI*
- releases: update to include 3.3.5
- releases: update to include 3.4.2
- rootfs-postcommands: amend systemd\_create\_users add user to group check
- ruby: update 3.0.2 -> 3.0.3
- scripts/runqemu-ifdown: Don't treat the last iptables command as special
- sdk: fix search for dynamic loader
- selftest: recipetool: Correct the URI for socat
- sstate: inside the threadedpool don't write to the shared localdata
- uninative: Upgrade to 3.5
- util-linux: upgrade to 2.37.4
- vim: Update to 8.2.4524 for further CVE fixes
- wic: Use custom kernel path if provided
- wireless-regdb: upgrade 2021.08.28 -> 2022.02.18
- zip: modify when match.S is built

### Contributors to 3.4.3

- Alexander Kanavin
- Anuj Mittal
- Bill Pittman
- Bruce Ashfield
- Chee Yang Lee
- Christian Eggers
- Daniel Gomez
- Daniel Müller

- Daniel Wagenknecht
- Florian Amstutz
- Joe Slater
- Jose Quaresma
- Justin Bronder
- Lee Chee Yang
- Michael Halstead
- Michael Opdenacker
- Oleksandr Ocheretnyi
- Oleksandr Suvorov
- Pavel Zhukov
- Peter Kjellerstedt
- Richard Purdie
- Robert Yang
- Ross Burton
- Sakib Sajal
- Saul Wold
- Sean Anderson
- Stefan Herbrechtsmeier
- Tamizharasan Kumar
- Tean Cunningham
- Zoltán Böszörményi
- pgowda
- Wang Mingyu

### **Repositories / Downloads for 3.4.3**

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: `honister`
- Tag: `yocto-3.4.3`
- Git Revision: `ee68ae307fd951b9de6b31dc6713ea29186b7749`
- Release Artefact: `poky-ee68ae307fd951b9de6b31dc6713ea29186b7749`
- sha: `92c3d73c3e74f0e1d5c2ab2836ce3a3accbe47772cea70df3755845e0db1379b`

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.3/poky-ee68ae307fd951b9de6b31dc6713ea29186b7749.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.3/poky-ee68ae307fd951b9de6b31dc6713ea29186b7749.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: `honister`
- Tag: `yocto-3.4.3`
- Git Revision: `ebca8f3ac9372b7ebb3d39e8f7f930b63b481448`
- Release Artefact: `oecore-ebca8f3ac9372b7ebb3d39e8f7f930b63b481448`
- sha: `f28e503f6f6c0bcd9192dbd528f8e3c7bcea504c089117e0094d9a4f315f4b9f`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.3/oecore-ebca8f3ac9372b7ebb3d39e8f7f930b63b481448.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.3/oecore-ebca8f3ac9372b7ebb3d39e8f7f930b63b481448.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: `honister`
- Tag: `yocto-3.4.3`
- Git Revision: `f5d761cbd5c957e4405c5d40b0c236d263c916a8`
- Release Artefact: `meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8`
- sha: `d4305d638ef80948584526c8ca386a8cf77933dff8a3b8da98d26a5c40fcc11`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.3/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.3/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: `honister`
- Tag: `yocto-3.4.3`
- Git Revision: `f04e4369bf9dd3385165281b9fa2ed1043b0e400`
- Release Artefact: `meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400`
- sha: `ef8e2b1ec1fb43dbec4ff6990ac736315c7bc2d8c8e79249e1d337558657d3fe`
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.3/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.3/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>

- Branch: 1.52
- Tag: yocto-3.4.3
- Git Revision: 43dcb2b2a2b95a5c959be57bca94fb7190ea6257
- Release Artefact: bitbake-43dcb2b2a2b95a5c959be57bca94fb7190ea6257
- sha: 92497ff97fed81dcc6d3e202969fb63ca983a8f5d9d91cafc6aee88312f79cf9
- Download Locations: <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.3/bitbake-43dcb2b2a2b95a5c959be57bca94fb7190ea6257.tar.bz2>, <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.3/bitbake-43dcb2b2a2b95a5c959be57bca94fb7190ea6257.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: honister
- Tag: yocto-3.4.3
- Git Revision: 15f46f97d9cad558c19fc1dc19cfbe3720271d04

## 17.12.6 Release notes for 3.4.4 (honister)

### Security Fixes in 3.4.4

- tiff: fix CVE-2022-0865, CVE-2022-0891, CVE-2022-0907, CVE-2022-0908, CVE-2022-0909 and CVE-2022-0924
- xz: fix CVE-2022-1271
- unzip: fix CVE-2021-4217
- zlib: fix CVE-2018-25032
- grub: ignore CVE-2021-46705

### Fixes in 3.4.4

- alsa-tools: Ensure we install correctly
- bitbake.conf: mark all directories as safe for git to read
- bitbake: knotty: display active tasks when printing keepAlive() message
- bitbake: knotty: reduce keep-alive timeout from 5000s (83 minutes) to 10 minutes
- bitbake: server/process: Disable gc around critical section
- bitbake: server/xmlrpcserver: Add missing xmlrpcclient import
- bitbake: toaster: Fix *IMAGE\_INSTALL* issues with *\_append* vs *:append*
- bitbake: toaster: fixtures replace gatesgarth
- build-appliance-image: Update to honister head revision
- conf.py/poky.yaml: Move version information to poky.yaml and read in conf.py



- conf/machine: fix QEMU x86 sound options
- devupstream: fix handling of *SRC\_URI*
- documentation: update for 3.4.4 release
- externalsrc/devtool: Fix to work with fixed export function flags handling
- gmp: add missing COPYINGv3
- gnu-config: update *SRC\_URI*
- libxml2: fix CVE-2022-23308 regression
- libxml2: move to gitlab.gnome.org
- libxml2: update to 2.9.13
- libxshmfence: Correct *LICENSE* to HPND
- license\_image.bbclass: close package.manifest file
- linux-firmware: correct license for ar3k firmware
- linux-firmware: upgrade 20220310 -> 20220411
- linux-yocto-rt/5.10: update to -rt61
- linux-yocto/5.10: cfg/debug: add configs for kcsan
- linux-yocto/5.10: split vtpm for more granular inclusion
- linux-yocto/5.10: update to v5.10.109
- linux-yocto: nohz\_full boot arg fix
- oe-pkgdata-util: Adapt to the new variable override syntax
- oeqa/selftest/devtool: ensure Git username is set before upgrade tests
- poky.conf: bump version for 3.4.4 release
- pseudo: Add patch to workaround paths with crazy lengths
- pseudo: Fix handling of absolute links
- sanity: Add warning for local hasheqiv server with remote sstate mirrors
- scripts/runqemu: Fix memory limits for qemux86-64
- shadow-native: Simplify and fix syslog disable patch
- tiff: Add marker for CVE-2022-1056 being fixed
- toaster: Fix broken overrides usage
- u-boot: Inherit pkgconfig
- uninative: Upgrade to 3.6 with gcc 12 support
- vim: Upgrade 8.2.4524 -> 8.2.4681
- virglrenderer: update *SRC\_URI*

- webkitgtk: update to 2.32.4
- wireless-regdb: upgrade 2022.02.18 -> 2022.04.08

### Known Issues

There were a couple of known autobuilder intermittent bugs that occurred during release testing but these are not regressions in the release.

### Contributors to 3.4.4

- Alexandre Belloni
- Anuj Mittal
- Bruce Ashfield
- Chee Yang Lee
- Dmitry Baryshkov
- Joe Slater
- Konrad Weihmann
- Martin Jansa
- Michael Opdenacker
- Minjae Kim
- Peter Kjellerstedt
- Ralph Siemsen
- Richard Purdie
- Ross Burton
- Tim Orling
- Wang Mingyu
- Zheng Ruoqin

### Repositories / Downloads for 3.4.4

poky

- Repository Location: <https://git.yoctoproject.org/poky>
- Branch: [honister](#)
- Tag: [yocto-3.4.4](#)
- Git Revision: [780eeec8851950ee6ac07a2a398ba937206bd2e4](#)
- Release Artefact: [poky-780eeec8851950ee6ac07a2a398ba937206bd2e4](#)
- sha: [09558927064454ec2492da376156b716d9fd14aae57196435d742db7bfd4b95](#)

- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.4/poky-780eeec8851950ee6ac07a2a398ba937206bd2e4.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.4/poky-780eeec8851950ee6ac07a2a398ba937206bd2e4.tar.bz2>

#### openembedded-core

- Repository Location: <https://git.openembedded.org/openembedded-core>
- Branch: honister
- Tag: yocto-3.4.4
- Git Revision: 1a6f5e27249afb6fb4d47c523b62b5dd2482a69d
- Release Artefact: oecore-1a6f5e27249afb6fb4d47c523b62b5dd2482a69d
- sha: b8354ca457756384139a579b9e51f1ba854013c99add90c0c4c6ef68421fed5
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.4/oecore-1a6f5e27249afb6fb4d47c523b62b5dd2482a69d.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.4/oecore-1a6f5e27249afb6fb4d47c523b62b5dd2482a69d.tar.bz2>

#### meta-mingw

- Repository Location: <https://git.yoctoproject.org/meta-mingw>
- Branch: honister
- Tag: yocto-3.4.4
- Git Revision: f5d761cbd5c957e4405c5d40b0c236d263c916a8
- Release Artefact: meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8
- sha: d4305d638ef80948584526c8ca386a8cf77933dff8a3b8da98d26a5c40fcc11
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.4/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.4/meta-mingw-f5d761cbd5c957e4405c5d40b0c236d263c916a8.tar.bz2>

#### meta-gplv2

- Repository Location: <https://git.yoctoproject.org/meta-gplv2>
- Branch: honister
- Tag: yocto-3.4.4
- Git Revision: f04e4369bf9dd3385165281b9fa2ed1043b0e400
- Release Artefact: meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400
- sha: ef8e2b1ec1fb43dbec4ff6990ac736315c7bc2d8c8e79249e1d337558657d3fe
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.4/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.4/meta-gplv2-f04e4369bf9dd3385165281b9fa2ed1043b0e400.tar.bz2>

#### bitbake

- Repository Location: <https://git.openembedded.org/bitbake>

- Branch: 1.52
- Tag: yocto-3.4.4
- Git Revision: c2d8f9b2137bd4a98eb0f51519493131773e7517
- Release Artefact: bitbake-c2d8f9b2137bd4a98eb0f51519493131773e7517
- sha: a8b6217f2d63975bbf49f430e11046608023ee2827faa893b15d9a0d702cf833
- Download                      Locations:                      <http://downloads.yoctoproject.org/releases/yocto/yocto-3.4.4/bitbake-c2d8f9b2137bd4a98eb0f51519493131773e7517.tar.bz2>,                      <http://mirrors.kernel.org/yocto/yocto/yocto-3.4.4/bitbake-c2d8f9b2137bd4a98eb0f51519493131773e7517.tar.bz2>

yocto-docs

- Repository Location: <https://git.yoctoproject.org/yocto-docs>
- Branch: honister
- Tag: yocto-3.4.4
- Git Revision: 5ead7d39aaf9044078dff27f462e29a8e31d89e4

## 17.13 Release 3.3 (hardknott)

This section provides migration information for moving to the Yocto Project 3.3 Release (codename "hardknott") from the prior release.

### 17.13.1 Minimum system requirements

You will now need at least Python 3.6 installed on your build host. Most recent distributions provide this, but should you be building on a distribution that does not have it, you can use the *buildtools* tarball (easily installable using `scripts/install-buildtools`) --- see *Versioni richieste di Git, tar, Python, make e gcc* for details.

### 17.13.2 Removed recipes

The following recipes have been removed:

- `go-dep`: obsolete with the advent of go modules
- `gst-validate`: replaced by `gst-devtools`
- `linux-yocto`: removed 5.8 version recipes (5.4 / 5.10 still provided)
- `vulkan-demos`: replaced by `vulkan-samples`

### 17.13.3 Single version common license file naming

Some license files in `meta/files/common-licenses` have been renamed to match current SPDX naming conventions:

- `AGPL-3.0` -> `AGPL-3.0-only`
- `GPL-1.0` -> `GPL-1.0-only`
- `GPL-2.0` -> `GPL-2.0-only`

- GPL-3.0 -> GPL-3.0-only
- LGPL-2.0 -> LGPL-2.0-only
- LGPL-2.1 -> LGPL-2.1-only
- LGPL-3.0 -> LGPL-3.0-only

Additionally, corresponding "-or-later" suffixed files have been added e.g. `GPL-2.0-or-later`.

It is not required that you change *LICENSE* values as there are mappings from the original names in place; however, in rare cases where you have a recipe which sets *LIC\_FILES\_CHKSUM* to point to file(s) in `meta/files/common-licenses` (which in any case is not recommended) you will need to update those.

### 17.13.4 New `python3targetconfig` class

A new *python3targetconfig* class has been created for situations where you would previously have inherited the *python3native* class but need access to target configuration data (such as correct installation directories). Recipes where this situation applies should be changed to inherit *python3targetconfig* instead of *python3native*. This also adds a dependency on target `python3`, so it should only be used where appropriate in order to avoid unnecessarily lengthening builds.

Some example recipes where this change has been made: `gpgme`, `libcap-ng`, `python3-pycairo`.

### 17.13.5 `setup.py` path for Python modules

In a Python module, sometimes `setup.py` can be buried deep in the source tree. Previously this was handled in recipes by setting *S* to point to the subdirectory within the source where `setup.py` is located. However with the recent *pseudo* changes, some Python modules make changes to files beneath `${S}`, for example:

```
S = "${WORKDIR}/git/python/pythonmodule"
```

then in `setup.py` it works with source code in a relative fashion, such as `../../src`. This causes *pseudo* to fail as it isn't able to track the paths properly. This release introduces a new `DISTUTILS_SETUP_PATH` variable so that recipes can specify it explicitly, for example:

```
S = "${WORKDIR}/git"
DISTUTILS_SETUP_PATH = "${S}/python/pythonmodule"
```

Recipes that inherit from `distutils3` (or *setuptools3* which itself inherits `distutils3`) that also set *S* to point to a Python module within a subdirectory in the aforementioned manner should be changed to set `DISTUTILS_SETUP_PATH` instead.

### 17.13.6 BitBake changes

- BitBake is now configured to use a default `umask` of `022` for all tasks (specified via a new *BB\_DEFAULT\_UMASK* variable). If needed, `umask` can still be set on a per-task basis via the `umask` varflag on the task function, but that is unlikely to be necessary in most cases.
- If a version specified in *PREFERRED\_VERSION* is not available this will now trigger a warning instead of just a note, making such issues more visible.

### 17.13.7 Packaging changes

The following packaging changes have been made; in all cases the main package still depends upon the split out packages so you should not need to do anything unless you want to take advantage of the improved granularity:

- `dbus`: `-common` and `-tools` split out
- `iproute2`: split `ip` binary to its own package
- `net-tools`: split `mii-tool` into its own package
- `procps`: split `ps` and `sysctl` into their own packages
- `rpm`: split build and extra functionality into separate packages
- `sudo`: split `sudo` binary into `sudo-sudo` and `libs` into `sudo-lib`
- `systemtap`: examples, Python scripts and runtime material split out
- `util-linux`: `libuuid` has been split out to its own `util-linux-libuuid` recipe (and corresponding packages) to avoid circular dependencies if `libgcrypt` support is enabled in `util-linux`. (`util-linux` depends upon `util-linux-libuuid`.)

### 17.13.8 Miscellaneous changes

- The default poky `DISTRO_VERSION` value now uses the core metadata's git hash (i.e. `METADATA_REVISION`) rather than the date (i.e. `DATE`) to reduce one small source of non-reproducibility. You can of course specify your own `DISTRO_VERSION` value as desired (particularly if you create your own custom distro configuration).
- `adwaita-icon-theme` version 3.34.3 has been added back, and is selected as the default via `PREFERRED_VERSION` in `meta/conf/distro/include/default-versions.inc` due to newer versions not working well with `librsvg` 2.40. `librsvg` is not practically upgradeable at the moment as it has been ported to Rust, and Rust is not (yet) in OE-Core, but this will change in a future release.
- `ffmpeg` is now configured to disable GPL-licensed portions by default to make it harder to accidentally violate the GPL. To explicitly enable GPL licensed portions, add `gpl` to `PACKAGECONFIG` for `ffmpeg` using a `bbappend` (or use `PACKAGECONFIG_append_pn-ffmpeg = " gpl "` in your configuration.)
- `connman` is now set to conflict with `systemd-networkd` as they overlap functionally and may interfere with each other at runtime.
- Canonical SPDX license names are now used in image license manifests in order to avoid aliases of the same license from showing up together (e.g. `GPLv2` and `GPL-2.0`)

## 17.14 Release 3.2 (gatesgarth)

This section provides migration information for moving to the Yocto Project 3.2 Release (codename "gatesgarth") from the prior release.

### 17.14.1 Minimum system requirements

gcc version 6.0 is now required at minimum on the build host. For older host distributions where this is not available, you can use the *buildtools-extended* tarball (easily installable using `scripts/install-buildtools`).

### 17.14.2 Removed recipes

The following recipes have been removed:

- `bjam-native`: replaced by `boost-build-native`
- `avahi-ui`: folded into the main `avahi` recipe --- the GTK UI can be disabled using *PACKAGECONFIG* for `avahi`.
- `build-compare`: no longer needed with the removal of the `packagefeed-stability` class
- `dhcp`: obsolete, functionally replaced by `dhcpcd` and `kea`
- `libmodulemd-v1`: replaced by `libmodulemd`
- `packagegroup-core-device-devel`: obsolete

### 17.14.3 Removed classes

The following classes (`.bbclass` files) have been removed:

- `spdx`: obsolete --- the Yocto Project is a strong supporter of SPDX, but this class was old code using a dated approach and had the potential to be misleading. The `meta-sdpsscanner` layer is a much more modern and active approach to handling this and is recommended as a replacement.
- `packagefeed-stability`: this class had become obsolete with the advent of hash equivalence and reproducible builds.

### 17.14.4 pseudo path filtering and mismatch behaviour

pseudo now operates on a filtered subset of files. This is a significant change to the way pseudo operates within OpenEmbedded --- by default, pseudo monitors and logs (adds to its database) any file created or modified whilst in a `fakeroot` environment. However, there are large numbers of files that we simply don't care about the permissions of whilst in that `fakeroot` context, for example `${S}`, `${B}`, `${T}`, `${SSTATE_DIR}`, the central `sstate` control directories, and others.

As of this release, new functionality in pseudo is enabled to ignore these directory trees (controlled using a new *PSEUDO\_IGNORE\_PATHS* variable) resulting in a cleaner database with less chance of "stray" mismatches if files are modified outside pseudo context. It also should reduce some overhead from pseudo as the interprocess round trip to the server is avoided.

There is a possible complication where some existing recipe may break, for example, a recipe was found to be writing to `${B}/install` for `make install` in *do\_install* and since `${B}` is listed as not to be tracked, there were errors trying to `chown root` for files in this location. Another example was the `tc1` recipe where the source directory *S* is set to a subdirectory of the source tree but files were written out to the directory structure above that subdirectory. For these types of cases in your own recipes, extend *PSEUDO\_IGNORE\_PATHS* to cover additional paths that pseudo should not be monitoring.

In addition, pseudo's behaviour on mismatches has now been changed --- rather than doing what turns out to be a rather dangerous "fixup" if it sees a file with a different path but the same inode as another file it has previously seen, pseudo will throw an `abort()` and direct you to a [wiki page](#) that explains how to deal with this.

### 17.14.5 `MLPREFIX` now required for multilib when runtime dependencies conditionally added

In order to solve some previously intractable problems with runtime dependencies and multilib, a change was made that now requires the `MLPREFIX` value to be explicitly prepended to package names being added as dependencies (e.g. in `RDEPENDS` and `RRECOMMENDS` values) where the dependency is conditionally added.

If you have anonymous Python or in-line Python conditionally adding dependencies in your custom recipes, and you intend for those recipes to work with multilib, then you will need to ensure that `${MLPREFIX}` is prefixed on the package names in the dependencies, for example (from the `glibc` recipe):

```
RRECOMMENDS_${PN} = "${@bb.utils.contains('DISTRO_FEATURES', 'ldconfig', '$  
↪${MLPREFIX}ldconfig', '', d)}"
```

This also applies when conditionally adding packages to `PACKAGES` where those packages have dependencies, for example (from the `alsa-plugins` recipe):

```
PACKAGES += "${@bb.utils.contains('PACKAGECONFIG', 'pulseaudio', 'alsa-plugins-  
↪pulseaudio-conf', '', d)}"  
...  
RDEPENDS_${PN}-pulseaudio-conf += "  
    ${MLPREFIX}libasound-module-conf-pulse \  
    ${MLPREFIX}libasound-module-ctl-pulse \  
    ${MLPREFIX}libasound-module-pcm-pulse \  
"
```

### 17.14.6 `packagegroup-core-device-devel` no longer included in images built for `qemu*` machines

`packagegroup-core-device-devel` was previously added automatically to images built for `qemu*` machines, however the purpose of the group and what it should contain is no longer clear, and in general, adding userspace development items to images is best done at the image/class level; thus this packagegroup was removed.

This packagegroup previously pulled in the following:

- `distcc-config`
- `nfs-export-root`
- `bash`
- `binutils-symlinks`

If you still need any of these in your image built for a `qemu*` machine then you will add them explicitly to `IMAGE_INSTALL` or another appropriate place in the dependency chain for your image (if you have not already done so).



### 17.14.7 DHCP server/client replaced

The `dhcp` software package has become unmaintained and thus has been functionally replaced by `dhcpcd` (client) and `kea` (server). You will need to replace references to the recipe/package names as appropriate --- most commonly, at the package level `dhcp-client` should be replaced by `dhcpcd` and `dhcp-server` should be replaced by `kea`. If you have any custom configuration files for these they will need to be adapted --- refer to the upstream documentation for `dhcpcd` and `kea` for further details.

### 17.14.8 Packaging changes

- `python3`: the `urllib` Python package has now moved into the core package, as it is used more commonly than just `netclient` (e.g. email, xml, mimetypes, pydoc). In addition, the `pathlib` module is now also part of the core package.
- `iptables`: `iptables-apply` and `ip6tables-apply` have been split out to their own package to avoid a `bash` dependency in the main `iptables` package

### 17.14.9 Package QA check changes

Previously, the following package QA checks triggered warnings, however they can be indicators of genuine underlying problems and are therefore now treated as errors:

- *already-stripped*
- *compile-host-path*
- *installed-vs-shipped*
- *ldflags*
- *pn-overrides*
- *rpaths*
- *staticdev*
- *unknown-configure-option*
- *useless-rpaths*

In addition, the following new checks were added and default to triggering an error:

- *shebang-size*: Check for shebang (`#!`) lines longer than 128 characters, which can give an error at runtime depending on the operating system.
- *unhandled-features-check*: Check if any of the variables supported by the *features\_check* class is set while not inheriting the class itself.
- *missing-update-alternatives*: Check if the recipe sets the *ALTERNATIVE* variable for any of its packages, and does not inherit the *update-alternatives* class.
- A trailing slash or duplicated slashes in the value of *S* or *B* will now trigger a warning so that they can be removed and path comparisons can be more reliable --- remove any instances of these in your recipes if the warning is displayed.

### 17.14.10 Globbing no longer supported in `file://` entries in `SRC_URI`

Globbing (`*` and `?` wildcards) in `file://` URLs within `SRC_URI` did not properly support file checksums, thus changes to the source files would not always change the `do_fetch` task checksum, and consequently would not ensure that the changed files would be incorporated in subsequent builds.

Unfortunately it is not practical to make globbing work generically here, so the decision was taken to remove support for globs in `file://` URLs. If you have any usage of these in your recipes, then you will now need to either add each of the files that you expect to match explicitly, or alternatively if you still need files to be pulled in dynamically, put the files into a subdirectory and reference that instead.

### 17.14.11 `deploy` class now cleans `DEPLOYDIR` before `do_deploy`

`do_deploy` as implemented in the `deploy` class now cleans up `${DEPLOYDIR}` before running, just as `do_install` cleans up `${D}` before running. This reduces the risk of `DEPLOYDIR` being accidentally contaminated by files from previous runs, possibly even with different config, in case of incremental builds.

Most recipes and classes that inherit the `deploy` class or interact with `do_deploy` are unlikely to be affected by this unless they add `prefuncs` to `do_deploy` which also put files into `${DEPLOYDIR}` --- these should be refactored to use `do_deploy_prepend` instead.

### 17.14.12 Custom SDK / SDK-style recipes need to include `nativesdk-sdk-provides-dummy`

All `nativesdk` packages require `/bin/sh` due to their postinstall scriptlets, thus this package has to be dummy-provided within the SDK and `nativesdk-sdk-provides-dummy` now does this. If you have a custom SDK recipe (or your own SDK-style recipe similar to e.g. `buildtools-tarball`), you will need to ensure `nativesdk-sdk-provides-dummy` or an equivalent is included in `TOOLCHAIN_HOST_TASK`.

### 17.14.13 `ld.so.conf` now moved back to main `glibc` package

There are cases where one doesn't want `ldconfig` on target (e.g. for read-only root filesystems, it's rather pointless), yet one still needs `/etc/ld.so.conf` to be present at image build time:

When some recipe installs libraries to a non-standard location, and therefore installs in a file in `/etc/ld.so.conf.d/foo.conf`, we need `/etc/ld.so.conf` containing:

```
include /etc/ld.so.conf.d/*.conf
```

in order to get those other locations picked up.

Thus `/etc/ld.so.conf` is now in the main `glibc` package so that there's always an `ld.so.conf` present when the build-time `ldconfig` runs towards the end of image construction.

The `ld.so.conf` and `ld.so.conf.d/*.conf` files do not take up significant space (at least not compared to the ~700kB `ldconfig` binary), and they might be needed in case `ldconfig` is installable, so they are left in place after the image is built. Technically it would be possible to remove them if desired, though it would not be trivial if you still wanted the build-time `ldconfig` to function (`ROOTFS_POSTPROCESS_COMMAND` will not work as `ldconfig` is run after the functions referred to by that variable).

#### 17.14.14 Host DRI drivers now used for GL support within `runqemu`

`runqemu` now uses the mesa-native libraries everywhere `virgl` is used (i.e. when `gl`, `gl-es` or `egl-headless` options are specified), but instructs them to load DRI drivers from the host. Unfortunately this may not work well with proprietary graphics drivers such as those from Nvidia; if you are using such drivers then you may need to switch to an alternative (such as Nouveau in the case of Nvidia hardware) or avoid using the GL options.

#### 17.14.15 Initramfs images now use a blank suffix

The reference *Initramfs* images (`core-image-minimal-initramfs`, `core-image-tiny-initramfs` and `core-image-testmaster-initramfs`) now set an empty string for *IMAGE\_NAME\_SUFFIX*, which otherwise defaults to `".rootfs"`. These images aren't root filesystems and thus the `rootfs` label didn't make sense. If you are looking for the output files generated by these image recipes directly then you will need to adapt to the new naming without the `.rootfs` part.

#### 17.14.16 Image artifact name variables now centralised in `image-artifact-names` class

The defaults for the following image artifact name variables have been moved from `bitbake.conf` to a new `image-artifact-names` class:

- *IMAGE\_BASENAME*
- *IMAGE\_LINK\_NAME*
- *IMAGE\_NAME*
- *IMAGE\_NAME\_SUFFIX*
- *IMAGE\_VERSION\_SUFFIX*

Image-related classes now inherit this class, and typically these variables are only referenced within image recipes so those will be unaffected by this change. However if you have references to these variables in either a recipe that is not an image or a class that is enabled globally, then those will now need to be changed to `inherit image-artifact-names`.

#### 17.14.17 Miscellaneous changes

- Support for the long-deprecated `PACKAGE_GROUP` variable has now been removed --- replace any remaining instances with *FEATURE\_PACKAGES*.
- The `FILESPATHPKG` variable, having been previously deprecated, has now been removed. Replace any remaining references with appropriate use of *FILESEXTRAPATHS*.
- Erroneous use of `inherit +=` (instead of `INHERIT +=`) in a configuration file now triggers an error instead of silently being ignored.
- `pptest` support has been removed from the `kbd` recipe, as upstream has moved to `autotest` which is difficult to work with in a cross-compilation environment.
- `oe.utils.is_machine_specific()` and `oe.utils.machine_paths()` have been removed as their utility was questionable. In the unlikely event that you have references to these in your own code, then the code will need to be reworked.

- The `i2ctransfer` module is now disabled by default when building `busybox` in order to be consistent with disabling the other `i2c` tools there. If you do wish the `i2ctransfer` module to be built in `BusyBox` then add `CONFIG_I2CTRANSFER=y` to your custom `BusyBox` configuration.
- In the `Upstream-Status` header convention for patches, `Accepted` has been replaced with `Backport` as these almost always mean the same thing i.e. the patch is already upstream and may need to be removed in a future recipe upgrade. If you are adding these headers to your own patches then use `Backport` to indicate that the patch has been sent upstream.
- The `tune-supersparc.inc` tune file has been removed as it does not appear to be widely used and no longer works.

## 17.15 Release 3.1 (dunfell)

This section provides migration information for moving to the Yocto Project 3.1 Release (codename "dunfell") from the prior release.

### 17.15.1 Minimum system requirements

The following versions / requirements of build host components have been updated:

- `gcc` 5.0
- `python` 3.5
- `tar` 1.28
- `rpcgen` is now required on the host (part of the `libc-dev-bin` package on Ubuntu, Debian and related distributions, and the `glibc` package on RPM-based distributions).

Additionally, the `makeinfo` and `pod2man` tools are *no longer* required on the host.

### 17.15.2 mpc8315e-rdb machine removed

The MPC8315E-RDB machine is old/obsolete and unobtainable, thus given the maintenance burden the `mpc8315e-rdb` machine configuration that supported it has been removed in this release. The removal does leave a gap in official PowerPC reference hardware support; this may change in future if a suitable machine with accompanying support resources is found.

### 17.15.3 Python 2 removed

Due to the expiration of upstream support in January 2020, support for Python 2 has now been removed; it is recommended that you use Python 3 instead. If absolutely needed there is a meta-python2 community layer containing Python 2, related classes and various Python 2-based modules, however it should not be considered as supported.

### 17.15.4 Reproducible builds now enabled by default

In order to avoid unnecessary differences in output files (aiding binary reproducibility), the Poky distribution configuration (`DISTRO = "poky"`) now inherits the `reproducible_build` class by default.

### 17.15.5 Impact of ptest feature is now more significant

The Poky distribution configuration (`DISTRO = "poky"`) enables ptests by default to enable runtime testing of various components. In this release, a dependency needed to be added that has resulted in a significant increase in the number of components that will be built just when building a simple image such as `core-image-minimal`. If you do not need runtime tests enabled for core components, then it is recommended that you remove "ptest" from `DISTRO_FEATURES` to save a significant amount of build time e.g. by adding the following in your configuration:

```
DISTRO_FEATURES_remove = "ptest"
```

### 17.15.6 Removed recipes

The following recipes have been removed:

- `chkconfig`: obsolete
- `console-tools`: obsolete
- `enchant`: replaced by `enchant2`
- `foomatic-filters`: obsolete
- `libidn`: no longer needed, moved to meta-oe
- `libmodulemd`: replaced by `libmodulemd-v1`
- `linux-yocto`: drop 4.19, 5.2 version recipes (5.4 now provided)
- `nspr`: no longer needed, moved to meta-oe
- `nss`: no longer needed, moved to meta-oe
- `python`: Python 2 removed (Python 3 preferred)
- `python-setuptools`: Python 2 version removed (python3-setuptools preferred)
- `sysprof`: no longer needed, moved to meta-oe
- `texi2html`: obsolete
- `u-boot-fw-utils`: functionally replaced by `libubootenv`

### 17.15.7 features\_check class replaces distro\_features\_check

The `distro_features_check` class has had its functionality expanded, now supporting `ANY_OF_MACHINE_FEATURES`, `REQUIRED_MACHINE_FEATURES`, `CONFLICT_MACHINE_FEATURES`, `ANY_OF_COMBINED_FEATURES`, `REQUIRED_COMBINED_FEATURES`, `CONFLICT_COMBINED_FEATURES`. As a result the class has now been renamed to `features_check`; the `distro_features_check` class still exists but generates a warning and redirects to the new class. In preparation for a future removal of the old class it is recommended that you update recipes currently inheriting `distro_features_check` to inherit `features_check` instead.

### 17.15.8 Removed classes

The following classes have been removed:

- `distutils-base`: moved to meta-python2
- `distutils`: moved to meta-python2
- `libc-common`: merged into the glibc recipe as nothing else used it.
- `python-dir`: moved to meta-python2
- `pythonnative`: moved to meta-python2
- `setuptools`: moved to meta-python2
- `tinderclient`: dropped as it was obsolete.

### 17.15.9 SRC\_URI checksum behaviour

Previously, recipes by tradition included both SHA256 and MD5 checksums for remotely fetched files in `SRC_URI`, even though only one is actually mandated. However, the MD5 checksum does not add much given its inherent weakness; thus when a checksum fails only the SHA256 sum will now be printed. The md5sum will still be verified if it is specified.

### 17.15.10 npm fetcher changes

The npm fetcher has been completely reworked in this release. The npm fetcher now only fetches the package source itself and no longer the dependencies; there is now also an npmsw fetcher which explicitly fetches the shrinkwrap file and the dependencies. This removes the slightly awkward `NPM_LOCKDOWN` and `NPM_SHRINKWRAP` variables which pointed to local files; the lockdown file is no longer needed at all. Additionally, the package name in `npm://` entries in `SRC_URI` is now specified using a `package` parameter instead of the earlier `name` which overlapped with the generic `name` parameter. All recipes using the npm fetcher will need to be changed as a result.

An example of the new scheme:

```
SRC_URI = "npm://registry.npmjs.org;package=array-flatten;version=1.1.1 \  
          npmsw://${THISDIR}/npm-shrinkwrap.json"
```

Another example where the sources are fetched from git rather than an npm repository:

```
SRC_URI = "git://github.com/foo/bar.git;protocol=https \  
          npmsw://${THISDIR}/npm-shrinkwrap.json"
```

devtool and recipetool have also been updated to match with the npm fetcher changes. Other than producing working and more complete recipes for npm sources, there is also a minor change to the command line for devtool: the `--fetch-dev` option has been renamed to `--npm-dev` as it is npm-specific.

### 17.15.11 Packaging changes

- `intltool` has been removed from `packagegroup-core-sdk` as it is rarely needed to build modern software --- `gettext` can do most of the things it used to be needed for. `intltool` has also been removed from `packagegroup-core-self-hosted` as it is not needed to for standard builds.
- `git`: `git-am`, `git-difftool`, `git-submodule`, and `git-request-pull` are no longer perl-based, so are now installed with the main `git` package instead of within `git-perltools`.
- The `ldconfig` binary built as part of `glibc` has now been moved to its own `ldconfig` package (note no `glibc-` prefix). This package is in the *[RRECOMMENDS](#)* of the main `glibc` package if `ldconfig` is present in *[DISTRO\\_FEATURES](#)*.
- `libevent` now splits each shared library into its own package (as Debian does). Since these are shared libraries and will be pulled in through the normal shared library dependency handling, there should be no impact to existing configurations other than less unnecessary libraries being installed in some cases.
- `linux-firmware` now has a new package for `bcm4366c` and includes available NVRAM config files into the `bcm43340`, `bcm43362`, `bcm43430` and `bcm4356-pcie` packages.
- `harfbuzz` now splits the new `libharfbuzz-subset.so` library into its own package to reduce the main package size in cases where `libharfbuzz-subset.so` is not needed.

### 17.15.12 Additional warnings

Warnings will now be shown at *[do\\_package\\_qa](#)* time in the following circumstances:

- A recipe installs `.desktop` files containing `MimeType` keys but does not inherit the new *[mime-xdg](#)* class
- A recipe installs `.xml` files into `${datadir}/mime/packages` but does not inherit the *[mime](#)* class

### 17.15.13 `wic` image type now used instead of `live` by default for x86

`conf/machine/include/x86-base.inc` (inherited by most x86 machine configurations) now specifies `wic` instead of `live` by default in *[IMAGE\\_FSTYPES](#)*. The `live` image type will likely be removed in a future release so it is recommended that you use `wic` instead.

### 17.15.14 Miscellaneous changes

- The undocumented `SRC_DISTRIBUTE_LICENSES` variable has now been removed in favour of a new `AVAILABLE_LICENSES` variable which is dynamically set based upon license files found in `${COMMON_LICENSE_DIR}` and `${LICENSE_PATH}`.
- The tune definition for big-endian microblaze machines is now `microblaze` instead of `microblazeeb`.
- `newlib` no longer has built-in syscalls. `libgloss` should then provide the syscalls, `crt0.o` and other functions that are no longer part of `newlib` itself. If you are using `TCLIBC = "newlib"` this now means that you must link applications with both `newlib` and `libgloss`, whereas before `newlib` would run in many configurations by itself.

## 17.16 Release 3.0 (zeus)

This section provides migration information for moving to the Yocto Project 3.0 Release (codename "zeus") from the prior release.

### 17.16.1 Init System Selection

Changing the init system manager previously required setting a number of different variables. You can now change the manager by setting the `INIT_MANAGER` variable and the corresponding include files (i.e. `conf/distro/include/init-manager-*.conf`). Include files are provided for four values: "none", "sysvinit", "systemd", and "mdev-busybox". The default value, "none", for `INIT_MANAGER` should allow your current settings to continue working. However, it is advisable to explicitly set `INIT_MANAGER`.

### 17.16.2 LSB Support Removed

Linux Standard Base (LSB) as a standard is not current, and is not well suited for embedded applications. Support can be continued in a separate layer if needed. However, presently LSB support has been removed from the core.

As a result of this change, the `poky-lsb` derivative distribution configuration that was also used for testing alternative configurations has been replaced with a `poky-altcfg` distribution that has LSB parts removed.

### 17.16.3 Removed Recipes

The following recipes have been removed.

- `core-image-lsb-dev`: Part of removed LSB support.
- `core-image-lsb`: Part of removed LSB support.
- `core-image-lsb-sdk`: Part of removed LSB support.
- `cve-check-tool`: Functionally replaced by the `cve-update-db` recipe and `cve-check` class.
- `eglinfno`: No longer maintained. `eglinfno` from `mesa-demos` is an adequate and maintained alternative.
- `gcc-8.3`: Version 8.3 removed. Replaced by 9.2.
- `gnome-themes-standard`: Only needed by `gtk+ 2.x`, which has been removed.
- `gtk+`: GTK+ 2 is obsolete and has been replaced by `gtk+3`.
- `irda-utils`: Has become obsolete. IrDA support has been removed from the Linux kernel in version 4.17 and later.
- `libnewt-python`: `libnewt` Python support merged into main `libnewt` recipe.
- `libsdl`: Replaced by newer `libsdl2`.
- `libx11-diet`: Became obsolete.
- `libxx86dga`: Removed obsolete client library.
- `libxx86misc`: Removed. Library is redundant.
- `linux-yocto`: Version 5.0 removed, which is now redundant (5.2 / 4.19 present).
- `lsbinitscripts`: Part of removed LSB support.



- `lsb`: Part of removed LSB support.
- `lsbtest`: Part of removed LSB support.
- `openssl10`: Replaced by newer `openssl` version 1.1.
- `packagegroup-core-lsb`: Part of removed LSB support.
- `python-nose`: Removed the Python 2.x version of the recipe.
- `python-numpy`: Removed the Python 2.x version of the recipe.
- `python-scons`: Removed the Python 2.x version of the recipe.
- `source-highlight`: No longer needed.
- `stress`: Replaced by `stress-ng`.
- `vulkan`: Split into `vulkan-loader`, `vulkan-headers`, and `vulkan-tools`.
- `weston-conf`: Functionality moved to `weston-init`.

## 17.16.4 Packaging Changes

The following packaging changes have occurred.

- The `Epiphany` browser has been dropped from `packagegroup-self-hosted` as it has not been needed inside `build-appliance-image` for quite some time and was causing resource problems.
- `libcap-ng` Python support has been moved to a separate `libcap-ng-python` recipe to streamline the build process when the Python bindings are not needed.
- `libdrm` now packages the file `amdgpu.ids` into a separate `libdrm-amdgpu` package.
- `python3`: The `runpy` module is now in the `python3-core` package as it is required to support the common "`python3 -m`" command usage.
- `distcc` now provides separate `distcc-client` and `distcc-server` packages as typically one or the other are needed, rather than both.
- `python*-setuptools` recipes now separately package the `pkg_resources` module in a `python-pkg-resources` / `python3-pkg-resources` package as the module is useful independent of the rest of the `setuptools` package. The main `python-setuptools` / `python3-setuptools` package depends on this new package so you should only need to update dependencies unless you want to take advantage of the increased granularity.

## 17.16.5 CVE Checking

`cve-check-tool` has been functionally replaced by a new `cve-update-db` recipe and functionality built into the `cve-check` class. The result uses NVD JSON data feeds rather than the deprecated XML feeds that `cve-check-tool` was using, supports CVSSv3 scoring, and makes other improvements.

Additionally, the `CVE_CHECK_CVE_WHITELIST` variable has been replaced by `CVE_CHECK_WHITELIST` (replaced by `CVE_CHECK_IGNORE` in version 4.0).

## 17.16.6 BitBake Changes

The following BitBake changes have occurred.

- `addtask` statements now properly validate dependent tasks. Previously, an invalid task was silently ignored. With this change, the invalid task generates a warning.
- Other invalid `addtask` and `deltask` usages now trigger these warnings: "multiple target tasks arguments with `addtask / deltask`", and "multiple before/after clauses".
- The "multiconfig" prefix is now shortened to "mc". "multiconfig" will continue to work, however it may be removed in a future release.
- The `bitbake -g` command no longer generates a `recipe-depends.dot` file as the contents (i.e. a reprocessed version of `task-depends.dot`) were confusing.
- The `bb.build.FuncFailed` exception, previously raised by `bb.build.exec_func()` when certain other exceptions have occurred, has been removed. The real underlying exceptions will be raised instead. If you have calls to `bb.build.exec_func()` in custom classes or `tinifol-using` scripts, any references to `bb.build.FuncFailed` should be cleaned up.
- Additionally, the `bb.build.exec_func()` no longer accepts the "pythonexception" parameter. The function now always raises exceptions. Remove this argument in any calls to `bb.build.exec_func()` in custom classes or scripts.
- The `BB_SETSCENE_VERIFY_FUNCTION2` variable is no longer used. In the unlikely event that you have any references to it, they should be removed.
- The `RunQueueExecuteScenequeue` and `RunQueueExecuteTasks` events have been removed since `setscene` tasks are now executed as part of the normal runqueue. Any event handling code in custom classes or scripts that handles these two events need to be updated.
- The arguments passed to functions used with `BB_HASHCHECK_FUNCTION` have changed. If you are using your own custom hash check function, see <https://git.yoctoproject.org/poky/commit/?id=40a5e193c4ba45c928fccd899415ea56b5417725> for details.
- Task specifications in `BB_TASKDEPDATA` and class implementations used in signature generator classes now use "<fn>:<task>" everywhere rather than the "." delimiter that was being used in some places. This change makes it consistent with all areas in the code. Custom signature generator classes and code that reads `BB_TASKDEPDATA` need to be updated to use ':' as a separator rather than '.'.

## 17.16.7 Sanity Checks

The following sanity check changes occurred.

- `SRC_URI` is now checked for usage of two problematic items:
  - "\${PN}" prefix/suffix use --- warnings always appear if `{PN}` is used. You must fix the issue regardless of whether multiconfig or anything else that would cause prefixing/suffixing to happen.
  - Github archive tarballs --- these are not guaranteed to be stable. Consequently, it is likely that the tarballs will be refreshed and thus the `SRC_URI` checksums will fail to apply. It is recommended that you fetch either an official release tarball or a specific revision from the actual Git repository instead.

Either one of these items now trigger a warning by default. If you wish to disable this check, remove `src-uri-bad` from `WARN_QA`.

- The `file-rdeps` runtime dependency check no longer expands `RDEPENDS` recursively as there is no mechanism to ensure they can be fully computed, and thus races sometimes result in errors either showing up or not. Thus, you might now see errors for missing runtime dependencies that were previously satisfied recursively. Here is an example: package A contains a shell script starting with `#!/bin/bash` but has no dependency on `bash`. However, package A depends on package B, which does depend on `bash`. You need to add the missing dependency or dependencies to resolve the warning.
- Setting `DEPENDS_${PN}` anywhere (i.e. typically in a recipe) now triggers an error. The error is triggered because `DEPENDS` is not a package-specific variable unlike `RDEPENDS`. You should set `DEPENDS` instead.
- `systemd` currently does not work well with the `musl` C library because only upstream officially supports linking the library with `glibc`. Thus, a warning is shown when building `systemd` in conjunction with `musl`.

## 17.16.8 Miscellaneous Changes

The following miscellaneous changes have occurred.

- The `gnome` class has been removed because it now does very little. You should update recipes that previously inherited this class to do the following:

```
inherit gnomebase gtk-icon-cache gconf mime
```

- The `meta/recipes-kernel/linux/linux-dtb.inc` file has been removed. This file was previously deprecated in favor of setting `KERNEL_DEVICETREE` in any kernel recipe and only produced a warning. Remove any `include` or `require` statements pointing to this file.
- `TARGET_CFLAGS`, `TARGET_CPPFLAGS`, `TARGET_CXXFLAGS`, and `TARGET_LDFLAGS` are no longer exported to the external environment. This change did not require any changes to core recipes, which is a good indicator that no changes will be required. However, if for some reason the software being built by one of your recipes is expecting these variables to be set, then building the recipe will fail. In such cases, you must either export the variable or variables in the recipe or change the scripts so that exporting is not necessary.
- You must change the host distro identifier used in `NATIVELSBSTRING` to use all lowercase characters even if it does not contain a version number. This change is necessary only if you are not using `uninative` and `SANITY_TESTED_DISTROS`.
- In the `base-files` recipe, writing the hostname into `/etc/hosts` and `/etc/hostname` is now done within the main `do_install` function rather than in the `do_install_basefilesissue` function. The reason for the change is because `do_install_basefilesissue` is more easily overridden without having to duplicate the hostname functionality. If you have done the latter (e.g. in a `base-files` `bbappend`), then you should remove it from your customized `do_install_basefilesissue` function.
- The `wic --expand` command now uses commas to separate "key:value" pairs rather than hyphens.

**i Nota**

The wic command-line help is not updated.

You must update any scripts or commands where you use `wic --expand` with multiple "key:value" pairs.

- UEFI image variable settings have been moved from various places to a central `conf/image-uefi.conf`. This change should not influence any existing configuration as the `meta/conf/image-uefi.conf` in the core metadata sets defaults that can be overridden in the same manner as before.
- `conf/distro/include/world-broken.inc` has been removed. For cases where certain recipes need to be disabled when using the musl C library, these recipes now have `COMPATIBLE_HOST_libc-musl` set with a comment that explains why.

## 17.17 Release 2.7 (warrior)

This section provides migration information for moving to the Yocto Project 2.7 Release (codename "warrior") from the prior release.

### 17.17.1 BitBake Changes

The following changes have been made to BitBake:

- BitBake now checks anonymous Python functions and pure Python functions (e.g. `def funcname:`) in the metadata for tab indentation. If found, BitBake produces a warning.
- BitBake now checks `BBFILE_COLLECTIONS` for duplicate entries and triggers an error if any are found.

### 17.17.2 Eclipse Support Removed

Support for the Eclipse IDE has been removed. Support continues for those releases prior to 2.7 that did include support. The 2.7 release does not include the Eclipse Yocto plugin.

### 17.17.3 qemu-native Splits the System and User-Mode Parts

The system and user-mode parts of `qemu-native` are now split. `qemu-native` provides the user-mode components and `qemu-system-native` provides the system components. If you have recipes that depend on QEMU's system emulation functionality at build time, they should now depend upon `qemu-system-native` instead of `qemu-native`.

### 17.17.4 The `upstream-tracking.inc` File Has Been Removed

The previously deprecated `upstream-tracking.inc` file is now removed. Any `UPSTREAM_TRACKING*` variables are now set in the corresponding recipes instead.

Remove any references you have to the `upstream-tracking.inc` file in your configuration.

### 17.17.5 The `DISTRO_FEATURES_LIBC` Variable Has Been Removed

The `DISTRO_FEATURES_LIBC` variable is no longer used. The ability to configure `glibc` using `kconfig` has been removed for quite some time making the `libc-*` features set no longer effective.

Remove any references you have to `DISTRO_FEATURES_LIBC` in your own layers.

### 17.17.6 License Value Corrections

The following corrections have been made to the *LICENSE* values set by recipes:

- *socat*: Corrected *LICENSE* to be "GPLv2" rather than "GPLv2+".
- *libgfortran*: Set license to "GPL-3.0-with-GCC-exception".
- *elfutils*: Removed "Elfutils-Exception" and set to "GPLv2" for shared libraries

### 17.17.7 Packaging Changes

This section provides information about packaging changes.

- *bind*: The `nsupdate` binary has been moved to the `bind-utils` package.
- *Debug split*: The default debug split has been changed to create separate source packages (i.e. `package_name-dbg` and `package_name-src`). If you are currently using `dbg-pkgs` in *IMAGE\_FEATURES* to bring in debug symbols and you still need the sources, you must now also add `src-pkgs` to *IMAGE\_FEATURES*. Source packages remain in the target portion of the SDK by default, unless you have set your own value for *SDKIMAGE\_FEATURES* that does not include `src-pkgs`.
- *Mount all using util-linux*: `/etc/default/mountall` has moved into the `-mount` sub-package.
- *Splitting binaries using util-linux*: `util-linux` now splits each binary into its own package for fine-grained control. The main `util-linux` package pulls in the individual binary packages using the *RRECOMMENDS* and *RDEPENDS* variables. As a result, existing images should not see any changes assuming *NO\_RECOMMENDATIONS* is not set.
- *netbase/base-files*: `/etc/hosts` has moved from `netbase` to `base-files`.
- *tzdata*: The main package has been converted to an empty meta package that pulls in all `tzdata` packages by default.
- *lrzsz*: This package has been removed from `packagegroup-self-hosted` and `packagegroup-core-tools-testapps`. The X/Y/ZModem support is less likely to be needed on modern systems. If you are relying on these packagegroups to include the `lrzsz` package in your image, you now need to explicitly add the package.

### 17.17.8 Removed Recipes

The following recipes have been removed:

- *gcc*: Drop version 7.3 recipes. Version 8.3 now remains.
- *linux-yocto*: Drop versions 4.14 and 4.18 recipes. Versions 4.19 and 5.0 remain.
- *go*: Drop version 1.9 recipes. Versions 1.11 and 1.12 remain.

- *xvideo-tests*: Became obsolete.
- *libart-lgpl*: Became obsolete.
- *gtk-icon-utils-native*: These tools are now provided by gtk+3-native
- *gcc-cross-initial*: No longer needed. gcc-cross/gcc-crosssdk is now used instead.
- *gcc-crosssdk-initial*: No longer needed. gcc-cross/gcc-crosssdk is now used instead.
- *glibc-initial*: Removed because the benefits of having it for site\_config are currently outweighed by the cost of building the recipe.

### 17.17.9 Removed Classes

The following classes have been removed:

- *distutils-tools*: This class was never used.
- *bugzilla.bbclass*: Became obsolete.
- *distrodata*: This functionality has been replaced by a more modern tinfoil-based implementation.

### 17.17.10 Miscellaneous Changes

The following miscellaneous changes occurred:

- The `distro` subdirectory of the Poky repository has been removed from the top-level `scripts` directory.
- Perl now builds for the target using `perl-cross` for better maintainability and improved build performance. This change should not present any problems unless you have heavily customized your Perl recipe.
- `arm-tunes`: Removed the "-march" option if mcpu is already added.
- `update-alternatives`: Convert file renames to `PACKAGE_PREPROCESS_FUNCS`
- `base/pixbufcache`: Obsolete `sstatecompletions` code has been removed.
- `native` class: `RDEPENDS` handling has been enabled.
- `inetutils`: This recipe has rsh disabled.

## 17.18 Release 2.6 (thud)

This section provides migration information for moving to the Yocto Project 2.6 Release (codename "thud") from the prior release.

### 17.18.1 GCC 8.2 is Now Used by Default

The GNU Compiler Collection version 8.2 is now used by default for compilation. For more information on what has changed in the GCC 8.x release, see <https://gcc.gnu.org/gcc-8/changes.html>.

If you still need to compile with version 7.x, GCC 7.3 is also provided. You can select this version by setting the and can be selected by setting the `GCCVERSION` variable to "7.%" in your configuration.

## 17.18.2 Removed Recipes

The following recipes have been removed:

- *beecrypt*: No longer needed since moving to RPM 4.
- *bigreqsproto*: Replaced by *xorgproto*.
- *calibrateproto*: Removed in favor of *xinput*.
- *compositeproto*: Replaced by *xorgproto*.
- *damageproto*: Replaced by *xorgproto*.
- *dmxproto*: Replaced by *xorgproto*.
- *dri2proto*: Replaced by *xorgproto*.
- *dri3proto*: Replaced by *xorgproto*.
- *eee-acpi-scripts*: Became obsolete.
- *fixesproto*: Replaced by *xorgproto*.
- *fontproto*: Replaced by *xorgproto*.
- *fstests*: Became obsolete.
- *gccmakedep*: No longer used.
- *glproto*: Replaced by *xorgproto*.
- *gnome-desktop3*: No longer needed. This recipe has moved to *meta-oe*.
- *icon-naming-utils*: No longer used since the Sato theme was removed in 2016.
- *inputproto*: Replaced by *xorgproto*.
- *kbproto*: Replaced by *xorgproto*.
- *libusb-compat*: Became obsolete.
- *libuser*: Became obsolete.
- *libnfsidmap*: No longer an external requirement since *nfs-utils* 2.2.1. *libnfsidmap* is now integrated.
- *libxcalibrate*: No longer needed with *xinput*.
- *mktemp*: Became obsolete. The *mktemp* command is provided by both *busybox* and *coreutils*.
- *ossp-uuid*: Is not being maintained and has mostly been replaced by *uuid.h* in *util-linux*.
- *pax-utils*: No longer needed. Previous QA tests that did use this recipe are now done at build time.
- *pcmciautils*: Became obsolete.
- *pixz*: No longer needed. *xz* now supports multi-threaded compression.
- *presentproto*: Replaced by *xorgproto*.
- *randrproto*: Replaced by *xorgproto*.
- *recordproto*: Replaced by *xorgproto*.

- *renderproto*: Replaced by *xorgproto*.
- *resourceproto*: Replaced by *xorgproto*.
- *scrnsaverproto*: Replaced by *xorgproto*.
- *trace-cmd*: Became obsolete. *perf* replaced this recipe's functionality.
- *videoproto*: Replaced by *xorgproto*.
- *wireless-tools*: Became obsolete. Superseded by *iw*.
- *xcmiscproto*: Replaced by *xorgproto*.
- *xextproto*: Replaced by *xorgproto*.
- *xf86dgaproto*: Replaced by *xorgproto*.
- *xf86driproto*: Replaced by *xorgproto*.
- *xf86miscproto*: Replaced by *xorgproto*.
- *xf86-video-omapfb*: Became obsolete. Use kernel modesetting driver instead.
- *xf86-video-omap*: Became obsolete. Use kernel modesetting driver instead.
- *xf86vidmodeproto*: Replaced by *xorgproto*.
- *xineramaproto*: Replaced by *xorgproto*.
- *xproto*: Replaced by *xorgproto*.
- *yasm*: No longer needed since previous usages are now satisfied by *nasm*.

### 17.18.3 Packaging Changes

The following packaging changes have been made:

- *cmake*: *cmake.m4* and *toolchain* files have been moved to the main package.
- *iptables*: The *iptables* modules have been split into separate packages.
- *alsa-lib*: *libasound* is now in the main *alsa-lib* package instead of *libasound*.
- *glibc*: *libnss-db* is now in its own package along with a */var/db/makedbs.sh* script to update databases.
- *python* and *python3*: The main package has been removed from the recipe. You must install specific packages or *python-modules* / *python3-modules* for everything.
- *systemtap*: Moved *systemtap-exporter* into its own package.

### 17.18.4 XOrg Protocol dependencies

The *\*proto* upstream repositories have been combined into one "xorgproto" repository. Thus, the corresponding recipes have also been combined into a single *xorgproto* recipe. Any recipes that depend upon the older *\*proto* recipes need to be changed to depend on the newer *xorgproto* recipe instead.

For names of recipes removed because of this repository change, see the [Removed Recipes](#) section.



### 17.18.5 `distutils` and `distutils3` Now Prevent Fetching Dependencies During the `do_configure` Task

Previously, it was possible for Python recipes that inherited the `distutils` and `distutils3` classes to fetch code during the `do_configure` task to satisfy dependencies mentioned in `setup.py` if those dependencies were not provided in the sysroot (i.e. recipes providing the dependencies were missing from *DEPENDS*).

#### **i** Nota

This change affects classes beyond just the two mentioned (i.e. `distutils` and `distutils3`). Any recipe that inherits `distutils*` classes are affected. For example, the `setuptools` and `setuptools3` recipes are affected since they inherit the `distutils*` classes.

Fetching these types of dependencies that are not provided in the sysroot negatively affects the ability to reproduce builds. This type of fetching is now explicitly disabled. Consequently, any missing dependencies in Python recipes that use these classes now result in an error during the `do_configure` task.

### 17.18.6 `linux-yocto` Configuration Audit Issues Now Correctly Reported

Due to a bug, the kernel configuration audit functionality was not writing out any resulting warnings during the build. This issue is now corrected. You might notice these warnings now if you have a custom kernel configuration with a `linux-yocto` style kernel recipe.

### 17.18.7 Image/Kernel Artifact Naming Changes

The following changes have been made:

- Name variables (e.g. *IMAGE\_NAME*) use a new *IMAGE\_VERSION\_SUFFIX* variable instead of *DATETIME*. Using *IMAGE\_VERSION\_SUFFIX* allows easier and more direct changes.

The *IMAGE\_VERSION\_SUFFIX* variable is set in the `bitbake.conf` configuration file as follows:

```
IMAGE_VERSION_SUFFIX = "-${DATETIME}"
```

- Several variables have changed names for consistency:

| Old Variable Name                        | New Variable Name                     |
|------------------------------------------|---------------------------------------|
| =====                                    |                                       |
| <code>KERNEL_IMAGE_BASE_NAME</code>      | <code>KERNEL_IMAGE_NAME</code>        |
| <code>KERNEL_IMAGE_SYMLINK_NAME</code>   | <code>KERNEL_IMAGE_LINK_NAME</code>   |
| <code>MODULE_TARBALL_BASE_NAME</code>    | <code>MODULE_TARBALL_NAME</code>      |
| <code>MODULE_TARBALL_SYMLINK_NAME</code> | <code>MODULE_TARBALL_LINK_NAME</code> |
| <code>INITRAMFS_BASE_NAME</code>         | <code>INITRAMFS_NAME</code>           |

- The `MODULE_IMAGE_BASE_NAME` variable has been removed. The module tarball name is now controlled directly with the *MODULE\_TARBALL\_NAME* variable.
- The *KERNEL\_DTB\_NAME* and *KERNEL\_DTB\_LINK\_NAME* variables have been introduced to control kernel Device Tree Binary (DTB) artifact names instead of mangling `KERNEL_IMAGE_*` variables.

- The `KERNEL_FIT_NAME` and `KERNEL_FIT_LINK_NAME` variables have been introduced to specify the name of flattened image tree (FIT) kernel images similar to other deployed artifacts.
- The `MODULE_TARBALL_NAME` and `MODULE_TARBALL_LINK_NAME` variable values no longer include the "module-" prefix or ".tgz" suffix. These parts are now hardcoded so that the values are consistent with other artifact naming variables.
- Added the `INITRAMFS_LINK_NAME` variable so that the symlink can be controlled similarly to other artifact types.
- `INITRAMFS_NAME` now uses "`{PKG}-{PKGVER}-{PKGR}-{MACHINE}{IMAGE_VERSION_SUFFIX}`" instead of "`{PV}-{PR}-{MACHINE}-{DATETIME}`", which makes it consistent with other variables.

### 17.18.8 SERIAL\_CONSOLE Deprecated

The `SERIAL_CONSOLE` variable has been functionally replaced by the `SERIAL_CONSOLES` variable for some time. With the Yocto Project 2.6 release, `SERIAL_CONSOLE` has been officially deprecated.

`SERIAL_CONSOLE` will continue to work as before for the 2.6 release. However, for the sake of future compatibility, it is recommended that you replace all instances of `SERIAL_CONSOLE` with `SERIAL_CONSOLES`.

#### Nota

The only difference in usage is that `SERIAL_CONSOLES` expects entries to be separated using semicolons as compared to `SERIAL_CONSOLE`, which expects spaces.

### 17.18.9 Configure Script Reports Unknown Options as Errors

If the configure script reports an unknown option, this now triggers a QA error instead of a warning. Any recipes that previously got away with specifying such unknown options now need to be fixed.

### 17.18.10 Override Changes

The following changes have occurred:

- The `virtclass-native` and `virtclass-nativesdk` Overrides Have Been Removed: The `virtclass-native` and `virtclass-nativesdk` overrides have been deprecated since 2012 in favor of `class-native` and `class-nativesdk`, respectively. Both `virtclass-native` and `virtclass-nativesdk` are now dropped.

#### Nota

The `virtclass-multilib` overrides for multilib are still valid.

- The `forcevariable` Override Now Has a Higher Priority Than `libc` Overrides: The `forcevariable` override is documented to be the highest priority override. However, due to a long-standing quirk of how `OVERRIDES` is set, the `libc` overrides (e.g. `libc-glibc`, `libc-musl`, and so forth) erroneously had a higher priority. This issue is now corrected.

It is likely this change will not cause any problems. However, it is possible with some unusual configurations that you might see a change in behavior if you were relying on the previous behavior. Be sure to check how you use `forcevariable` and `libc-*` overrides in your custom layers and configuration files to ensure they make sense.

- The `build-${BUILD_OS}` Override Has Been Removed: The `build-${BUILD_OS}`, which is typically `build-linux`, override has been removed because building on a host operating system other than a recent version of Linux is neither supported nor recommended. Dropping the override avoids giving the impression that other host operating systems might be supported.
- The `"_remove"` operator now preserves whitespace. Consequently, when specifying list items to remove, be aware that leading and trailing whitespace resulting from the removal is retained.

See the ["Removal \(Override Style Syntax\)"](#) section in the BitBake User Manual for a detailed example.

### 17.18.11 systemd Configuration is Now Split Into `systemd-conf`

The configuration for the `systemd` recipe has been moved into a `systemd-conf` recipe. Moving this configuration to a separate recipe avoids the `systemd` recipe from becoming machine-specific for cases where machine-specific configurations need to be applied (e.g. for `qemu*` machines).

Currently, the new recipe packages the following files:

```
${sysconfdir}/machine-id
${sysconfdir}/systemd/coredump.conf
${sysconfdir}/systemd/journald.conf
${sysconfdir}/systemd/logind.conf
${sysconfdir}/systemd/system.conf
${sysconfdir}/systemd/user.conf
```

If you previously used `bbappend` files to append the `systemd` recipe to change any of the listed files, you must do so for the `systemd-conf` recipe instead.

### 17.18.12 Automatic Testing Changes

This section provides information about automatic testing changes:

- `TEST_IMAGE` Variable Removed: Prior to this release, you set the `TEST_IMAGE` variable to "1" to enable automatic testing for successfully built images. The `TEST_IMAGE` variable no longer exists and has been replaced by the `TESTIMAGE_AUTO` variable.
- Inheriting the `testimage` and `testsdk` classes: best practices now dictate that you use the `IMAGE_CLASSES` variable rather than the `INHERIT` variable when you inherit the `testimage` and `testsdk` classes used for automatic testing.

### 17.18.13 OpenSSL Changes

OpenSSL has been upgraded from 1.0 to 1.1. By default, this upgrade could cause problems for recipes that have both versions in their dependency chains. The problem is that both versions cannot be installed together at build time.

#### Nota

It is possible to have both versions of the library at runtime.

### 17.18.14 BitBake Changes

The server logfile `bitbake-cookerdaemon.log` is now always placed in the *Build Directory* instead of the current directory.

### 17.18.15 Security Changes

The Poky distribution now uses security compiler flags by default. Inclusion of these flags could cause new failures due to stricter checking for various potential security issues in code.

### 17.18.16 Post Installation Changes

You must explicitly mark post installs to defer to the target. If you want to explicitly defer a postinstall to first boot on the target rather than at root filesystem creation time, use `pkg_postinst_ontarget()` or call `postinst_intercept_delay_to_first_boot` from `pkg_postinst()`. Any failure of a `pkg_postinst()` script (including exit 1) triggers an error during the *do\_rootfs* task.

For more information on post-installation behavior, see the "*Post-Installation Scripts*" section in the Yocto Project Development Tasks Manual.

### 17.18.17 Python 3 Profile-Guided Optimization

The `python3` recipe now enables profile-guided optimization. Using this optimization requires a little extra build time in exchange for improved performance on the target at runtime. Additionally, the optimization is only enabled if the current *MACHINE* has support for user-mode emulation in QEMU (i.e. "qemu-usermode" is in *MACHINE\_FEATURES*, which it is by default).

If you wish to disable Python profile-guided optimization regardless of the value of *MACHINE\_FEATURES*, then ensure that *PACKAGECONFIG* for the `python3` recipe does not contain "pgo". You could accomplish the latter using the following at the configuration level:

```
PACKAGECONFIG_remove_pn-python3 = "pgo"
```

Alternatively, you can set *PACKAGECONFIG* using an append file for the `python3` recipe.

## 17.18.18 Miscellaneous Changes

The following miscellaneous changes occurred:

- Default to using the Thumb-2 instruction set for armv7a and above. If you have any custom recipes that build software that needs to be built with the ARM instruction set, change the recipe to set the instruction set as follows:

```
ARM_INSTRUCTION_SET = "arm"
```

- `run-postinsts` no longer uses `/etc/*-postinsts` for `dpkg/opkg` in favor of built-in postinst support. RPM behavior remains unchanged.
- The `NOISO` and `NOHDD` variables are no longer used. You now control building `*.iso` and `*.hddimg` image types directly by using the `IMAGE_FSTYPES` variable.
- The `scripts/contrib/mkefidisk.sh` has been removed in favor of `Wic`.
- `kernel-modules` has been removed from `RRECOMMENDS` for `qemumips` and `qemumips64` machines. Removal also impacts the `x86-base.inc` file.

### Nota

`genericx86` and `genericx86-64` retain `kernel-modules` as part of the `RRECOMMENDS` variable setting.

- The `LGPLv2_WHITELIST_GPL-3.0` variable has been removed. If you are setting this variable in your configuration, set or append it to the `WHITELIST_GPL-3.0` variable instead.
- `${ASNEEDED}` is now included in the `TARGET_LDFLAGS` variable directly. The remaining definitions from `meta/conf/distro/include/as-needed.inc` have been moved to corresponding recipes.
- Support for DSA host keys has been dropped from the OpenSSH recipes. If you are still using DSA keys, you must switch over to a more secure algorithm as recommended by OpenSSH upstream.
- The `dhcp` recipe now uses the `dhcpd6.conf` configuration file in `dhcpd6.service` for IPv6 DHCP rather than re-using `dhcpd.conf`, which is now reserved for IPv4.

## 17.19 Release 2.5 (sumo)

This section provides migration information for moving to the Yocto Project 2.5 Release (codename "sumo") from the prior release.

### 17.19.1 Packaging Changes

This section provides information about packaging changes that have occurred:

- `bind-libs`: The libraries packaged by the `bind` recipe are in a separate `bind-libs` package.
- `libfm-gtk`: The `libfm` GTK+ bindings are split into a separate `libfm-gtk` package.

- `flex-libfl`: The flex recipe splits out libfl into a separate `flex-libfl` package to avoid too many dependencies being pulled in where only the library is needed.
- `grub-efi`: The `grub-efi` configuration is split into a separate `grub-bootconf` recipe. However, the dependency relationship from `grub-efi` is through a virtual/`grub-bootconf` provider making it possible to have your own recipe provide the dependency. Alternatively, you can use a BitBake append file to bring the configuration back into the `grub-efi` recipe.
- *armv7a Legacy Package Feed Support*: Legacy support is removed for transitioning from `armv7a` to `armv7a-vfp-neon` in package feeds, which was previously enabled by setting `PKGARCHCOMPAT_ARMV7A`. This transition occurred in 2011 and active package feeds should by now be updated to the new naming.

### 17.19.2 Removed Recipes

The following recipes have been removed:

- `gcc`: The version 6.4 recipes are replaced by 7.x.
- `gst-player`: Renamed to `gst-examples` as per upstream.
- `hostap-utils`: This software package is obsolete.
- `latencytop`: This recipe is no longer maintained upstream. The last release was in 2009.
- `libpfm4`: The only file that requires this recipe is `oprofile`, which has been removed.
- `linux-yocto`: The version 4.4, 4.9, and 4.10 recipes have been removed. Versions 4.12, 4.14, and 4.15 remain.
- `man`: This recipe has been replaced by modern `man-db`.
- `mkelfimage`: This tool has been removed in the upstream coreboot project, and is no longer needed with the removal of the ELF image type.
- `nativesdk-postinst-intercept`: This recipe is not maintained.
- `neon`: This software package is no longer maintained upstream and is no longer needed by anything in OpenEmbedded-Core.
- `oprofile`: The functionality of this recipe is replaced by `perf` and keeping compatibility on an ongoing basis with `musl` is difficult.
- `pax`: This software package is obsolete.
- `stat`: This software package is not maintained upstream. `coreutils` provides a modern `stat` binary.
- `zisofs-tools-native`: This recipe is no longer needed because the compressed ISO image feature has been removed.

### 17.19.3 Scripts and Tools Changes

- `yocto-bsp`, `yocto-kernel`, and `yocto-layer`: The `yocto-bsp`, `yocto-kernel`, and `yocto-layer` scripts previously shipped with poky but not in OpenEmbedded-Core have been removed. These scripts are not maintained and are outdated. In many cases, they are also limited in scope. The `bitbake-layers create-layer` command is a direct replacement for `yocto-layer`. See the documentation to create a BSP or kernel recipe in the "*Esempio di Ricetta del Kernel BSP*" section.

- `devtool finish`: `devtool finish` now exits with an error if there are uncommitted changes or a rebase/am in progress in the recipe's source repository. If this error occurs, there might be uncommitted changes that will not be included in updates to the patches applied by the recipe. A `-f/--force` option is provided for situations that the uncommitted changes are inconsequential and you want to proceed regardless.
- `scripts/oe-setup-rpmrepo` script: The functionality of `scripts/oe-setup-rpmrepo` is replaced by `bitbake package-index`.
- `scripts/test-dependencies.sh` script: The script is largely made obsolete by the recipe-specific `sysroots` functionality introduced in the previous release.

## 17.19.4 BitBake Changes

- The `--runall` option has changed. There are two different behaviors people might want:
  - *Behavior A*: For a given target (or set of targets) look through the task graph and run task X only if it is present and will be built.
  - *Behavior B*: For a given target (or set of targets) look through the task graph and run task X if any recipe in the taskgraph has such a target, even if it is not in the original task graph.

The `--runall` option now performs "Behavior B". Previously `--runall` behaved like "Behavior A". A `--runonly` option has been added to retain the ability to perform "Behavior A".

- Several explicit "run this task for all recipes in the dependency tree" tasks have been removed (e.g. `fetchall`, `checkuriall`, and the `*all` tasks provided by the `distrodata` and `archiver` classes). There is a BitBake option to complete this for any arbitrary task. For example:

```
bitbake <target> -c fetchall
```

should now be replaced with:

```
bitbake <target> --runall=fetch
```

## 17.19.5 Python and Python 3 Changes

Here are auto-packaging changes to Python and Python 3:

The script-managed `python-*--manifest.inc` files that were previously used to generate Python and Python 3 packages have been replaced with a JSON-based file that is easier to read and maintain. A new task is available for maintainers of the Python recipes to update the JSON file when upgrading to new Python versions. You can now edit the file directly instead of having to edit a script and run it to update the file.

One particular change to note is that the Python recipes no longer have build-time provides for their packages. This assumes `python-foo` is one of the packages provided by the Python recipe. You can no longer run `bitbake python-foo` or have a *DEPENDS* on `python-foo`, but doing either of the following causes the package to work as expected:

```
IMAGE_INSTALL_append = " python-foo"
```

or

```
RDEPENDS_${PN} = "python-foo"
```

The earlier build-time provides behavior was a quirk of the way the Python manifest file was created. For more information on this change please see [this commit](#).

### 17.19.6 Miscellaneous Changes

- The *kernel* class supports building packages for multiple kernels. If your kernel recipe or `.bbappend` file mentions packaging at all, you should replace references to the kernel in package names with `${KERNEL_PACKAGE_NAME}`. For example, if you disable automatic installation of the kernel image using `RDEPENDS_kernel-base = ""` you can avoid warnings using `RDEPENDS_${KERNEL_PACKAGE_NAME}-base = ""` instead.
- The *buildhistory* class commits changes to the repository by default so you no longer need to set `BUILDHISTORY_COMMIT = "1"`. If you want to disable commits you need to set `BUILDHISTORY_COMMIT = "0"` in your configuration.
- The beaglebone reference machine has been renamed to `beaglebone-yocto`. The `beaglebone-yocto` BSP is a reference implementation using only mainline components available in `OpenEmbedded-Core` and `meta-yocto-bsp`, whereas Texas Instruments maintains a full-featured BSP in the `meta-ti` layer. This rename avoids the previous name clash that existed between the two BSPs.
- The *update-alternatives* class no longer works with `SysV init` scripts because this usage has been problematic. Also, the `syslogd` recipe no longer uses `update-alternatives` because it is incompatible with other implementations.
- By default, the *cmake* class uses `ninja` instead of `make` for building. This improves build performance. If a recipe is broken with `ninja`, then the recipe can set `OECMAKE_GENERATOR = "Unix Makefiles"` to change back to `make`.
- The previously deprecated `base_*` functions have been removed in favor of their replacements in `meta/lib/oe` and `bitbake/lib/bb`. These are typically used from recipes and classes. Any references to the old functions must be updated. The following table shows the removed functions and their replacements:



| <i>Removed</i>                            | <i>Replacement</i>                                                                |
|-------------------------------------------|-----------------------------------------------------------------------------------|
| <code>base_path_join()</code>             | <code>oe.path.join()</code>                                                       |
| <code>base_path_relative()</code>         | <code>oe.path.relative()</code>                                                   |
| <code>base_path_out()</code>              | <code>oe.path.format_display()</code>                                             |
| <code>base_read_file()</code>             | <code>oe.utils.read_file()</code>                                                 |
| <code>base_ifelse()</code>                | <code>oe.utils.ifelse()</code>                                                    |
| <code>base_conditional()</code>           | <code>oe.utils.conditional()</code>                                               |
| <code>base_less_or_equal()</code>         | <code>oe.utils.less_or_equal()</code>                                             |
| <code>base_version_less_or_equal()</code> | <code>oe.utils.version_less_or_equal()</code>                                     |
| <code>base_contains()</code>              | <code>bb.utils.contains()</code>                                                  |
| <code>base_both_contain()</code>          | <code>oe.utils.both_contain()</code>                                              |
| <code>base_prune_suffix()</code>          | <code>oe.utils.prune_suffix()</code>                                              |
| <code>oe_filter()</code>                  | <code>oe.utils.str_filter()</code>                                                |
| <code>oe_filter_out()</code>              | <code>oe.utils.str_filter_out()</code> (or use the <code>_remove</code> operator) |

- Using `exit 1` to explicitly defer a postinstall script until first boot is now deprecated since it is not an obvious mechanism and can mask actual errors. If you want to explicitly defer a postinstall to first boot on the target rather than at `rootfs` creation time, use `pkg_postinst_ontarget()` or call `postinst_intercept_delay_to_first_boot` from `pkg_postinst()`. Any failure of a `pkg_postinst()` script (including `exit 1`) will trigger a warning during `do_rootfs`.

For more information, see the "*Post-Installation Scripts*" section in the Yocto Project Development Tasks Manual.

- The `elf` image type has been removed. This image type was removed because the `mkelfimage` tool that was required to create it is no longer provided by coreboot upstream and required updating every time `binutils` updated.
- Support for `.iso` image compression (previously enabled through `COMPRESSISO = "1"`) has been removed. The userspace tools (`zisofs-tools`) are unmaintained and `squashfs` provides better performance and compression. In order to build a live image with `squashfs+lz4` compression enabled you should now set `LIVE_ROOTFS_TYPE = "squashfs-lz4"` and ensure that `live` is in *IMAGE\_FSTYPES*.
- Recipes with an unconditional dependency on `libpam` are only buildable with `pam` in *DISTRO\_FEATURES*. If the dependency is truly optional then it is recommended that the dependency be conditional upon `pam` being in *DISTRO\_FEATURES*.
- For EFI-based machines, the bootloader (`grub-efi` by default) is installed into the image at `/boot`. Wic can be used to split the bootloader into separate boot and root filesystem partitions if necessary.
- Patches whose context does not match exactly (i.e. where patch reports "fuzz" when applying) will generate a warning. For an example of this see [this commit](#).
- Layers are expected to set `LAYERSERIES_COMPAT_layername` to match the version(s) of OpenEmbedded-Core they are compatible with. This is specified as codenames using spaces to separate multiple values (e.g. "rocko sumo"). If a layer does not set `LAYERSERIES_COMPAT_layername`, a warning will be shown. If a layer sets a value that does not include the current version ("sumo" for the 2.5 release), then an error will be produced.

- The `TZ` environment variable is set to "UTC" within the build environment in order to fix reproducibility problems in some recipes.

## 17.20 Release 2.4 (rocko)

This section provides migration information for moving to the Yocto Project 2.4 Release (codename "rocko") from the prior release.

### 17.20.1 Memory Resident Mode

A persistent mode is now available in BitBake's default operation, replacing its previous "memory resident mode" (i.e. `oe-init-build-env-memres`). Now you only need to set `BB_SERVER_TIMEOUT` to a timeout (in seconds) and BitBake's server stays resident for that amount of time between invocations. The `oe-init-build-env-memres` script has been removed since a separate environment setup script is no longer needed.

### 17.20.2 Packaging Changes

This section provides information about packaging changes that have occurred:

- `python3` Changes:
  - The main "python3" package now brings in all of the standard Python 3 distribution rather than a subset. This behavior matches what is expected based on traditional Linux distributions. If you wish to install a subset of Python 3, specify `python-core` plus one or more of the individual packages that are still produced.
  - `python3`: The `bz2.py`, `lzma.py`, and `_compression.py` scripts have been moved from the `python3-misc` package to the `python3-compression` package.
- `binutils`: The `libbfd` library is now packaged in a separate "libbfd" package. This packaging saves space when certain tools (e.g. `perf`) are installed. In such cases, the tools only need `libbfd` rather than all the packages in `binutils`.
- `util-linux` Changes:
  - The `su` program is now packaged in a separate "util-linux-su" package, which is only built when "pam" is listed in the `DISTRO_FEATURES` variable. `util-linux` should not be installed unless it is needed because `su` is normally provided through the shadow file format. The main `util-linux` package has runtime dependencies (i.e. `RDEPENDS`) on the `util-linux-su` package when "pam" is in `DISTRO_FEATURES`.
  - The `switch_root` program is now packaged in a separate "util-linux-switch-root" package for small *Initramfs* images that do not need the whole `util-linux` package or the `busybox` binary, which are both much larger than `switch_root`. The main `util-linux` package has a recommended runtime dependency (i.e. `RRECOMMENDS`) on the `util-linux-switch-root` package.
  - The `ionice` program is now packaged in a separate "util-linux-ionice" package. The main `util-linux` package has a recommended runtime dependency (i.e. `RRECOMMENDS`) on the `util-linux-ionice` package.

- `initscripts`: The `sushell` program is now packaged in a separate "initscripts-sushell" package. This packaging change allows systems to pull `sushell` in when `selinux` is enabled. The change also eliminates needing to pull in the entire `initscripts` package. The main `initscripts` package has a runtime dependency (i.e. *RDEPENDS*) on the `sushell` package when "selinux" is in *DISTRO\_FEATURES*.
- `glib-2.0`: The `glib-2.0` package now has a recommended runtime dependency (i.e. *RRECOMMENDS*) on the `shared-mime-info` package, since large portions of GIO are not useful without the MIME database. You can remove the dependency by using the *BAD\_RECOMMENDATIONS* variable if `shared-mime-info` is too large and is not required.
- *Go Standard Runtime*: The Go standard runtime has been split out from the main `go` recipe into a separate `go-runtime` recipe.

### 17.20.3 Removed Recipes

- `acpitests`: This recipe is not maintained.
- `autogen-native`: No longer required by Grub, `oe-core`, or `meta-oe`.
- `bdwgc`: Nothing in OpenEmbedded-Core requires this recipe. It has moved to `meta-oe`.
- `byacc`: This recipe was only needed by `rpm 5.x` and has moved to `meta-oe`.
- `gcc (5.4)`: The 5.4 series dropped the recipe in favor of 6.3 / 7.2.
- `gnome-common`: Deprecated upstream and no longer needed.
- `go-bootstrap-native`: Go 1.9 does its own bootstrapping so this recipe has been removed.
- `guile`: This recipe was only needed by `autogen-native` and `remake`. The recipe is no longer needed by either of these programs.
- `libclass-isa-perl`: This recipe was previously needed for LSB 4, no longer needed.
- `libdumpvalue-perl`: This recipe was previously needed for LSB 4, no longer needed.
- `libenv-perl`: This recipe was previously needed for LSB 4, no longer needed.
- `libfile-checktree-perl`: This recipe was previously needed for LSB 4, no longer needed.
- `libi18n-collate-perl`: This recipe was previously needed for LSB 4, no longer needed.
- `libiconv`: This recipe was only needed for `uclibc`, which was removed in the previous release. `glibc` and `musl` have their own implementations. `meta-mingw` still needs `libiconv`, so it has been moved to `meta-mingw`.
- `libpng12`: This recipe was previously needed for LSB. The current `libpng` is 1.6.x.
- `libpod-plainer-perl`: This recipe was previously needed for LSB 4, no longer needed.
- `linux-yocto (4.1)`: This recipe was removed in favor of 4.4, 4.9, 4.10 and 4.12.
- `mailx`: This recipe was previously only needed for LSB compatibility, and upstream is defunct.
- `mesa (git version only)`: The git version recipe was stale with respect to the release version.
- `ofono (git version only)`: The git version recipe was stale with respect to the release version.
- `portmap`: This recipe is obsolete and is superseded by `rpcbind`.

- `python3-pygpme`: This recipe is old and unmaintained. It was previously required by `dnf`, which has switched to official `gpme` Python bindings.
- `python-async`: This recipe has been removed in favor of the Python 3 version.
- `python-gitdb`: This recipe has been removed in favor of the Python 3 version.
- `python-git`: This recipe was removed in favor of the Python 3 version.
- `python-mako`: This recipe was removed in favor of the Python 3 version.
- `python-pexpect`: This recipe was removed in favor of the Python 3 version.
- `python-ptyprocess`: This recipe was removed in favor of Python the 3 version.
- `python-pycurl`: Nothing is using this recipe in OpenEmbedded-Core (i.e. `meta-oe`).
- `python-six`: This recipe was removed in favor of the Python 3 version.
- `python-smmap`: This recipe was removed in favor of the Python 3 version.
- `remake`: Using `remake` as the provider of `virtual/make` is broken. Consequently, this recipe is not needed in OpenEmbedded-Core.

## 17.20.4 Kernel Device Tree Move

Kernel Device Tree support is now easier to enable in a kernel recipe. The Device Tree code has moved to a *kernel-devicetree* class. Functionality is automatically enabled for any recipe that inherits the *kernel* class and sets the *KERNEL\_DEVICETREE* variable. The previous mechanism for doing this, `meta/recipes-kernel/linux/linux-dtb.inc`, is still available to avoid breakage, but triggers a deprecation warning. Future releases of the Yocto Project will remove `meta/recipes-kernel/linux/linux-dtb.inc`. It is advisable to remove any `require` statements that request `meta/recipes-kernel/linux/linux-dtb.inc` from any custom kernel recipes you might have. This will avoid breakage in post 2.4 releases.

## 17.20.5 Package QA Changes

- The "unsafe-references-in-scripts" QA check has been removed.
- If you refer to `${COREBASE}/LICENSE` within *LIC\_FILES\_CHKSUM* you receive a warning because this file is a description of the license for OE-Core. Use `${COMMON_LICENSE_DIR}/MIT` if your recipe is MIT-licensed and you cannot use the preferred method of referring to a file within the source tree.

## 17.20.6 README File Changes

- The main Poky *README* file has been moved to the `meta-poky` layer and has been renamed `README.poky`. A symlink has been created so that references to the old location work.
- The `README.hardware` file has been moved to `meta-yocto-bsp`. A symlink has been created so that references to the old location work.
- A `README.qemu` file has been created with coverage of the `qemu*` machines.

## 17.20.7 Miscellaneous Changes

- The `ROOTFS_PKGMANAGE_BOOTSTRAP` variable and any references to it have been removed. You should remove this variable from any custom recipes.
- The `meta-yocto` directory has been removed.

### Nota

In the Yocto Project 2.1 release `meta-yocto` was renamed to `meta-poky` and the `meta-yocto` subdirectory remained to avoid breaking existing configurations.

- The `maintainers.inc` file, which tracks maintainers by listing a primary person responsible for each recipe in OE-Core, has been moved from `meta-poky` to OE-Core (i.e. from `meta-poky/conf/distro/include` to `meta/conf/distro/include`).
- The `buildhistory` class now makes a single commit per build rather than one commit per subdirectory in the repository. This behavior assumes the commits are enabled with `BUILDHISTORY_COMMIT = "1"`, which is typical. Previously, the `buildhistory` class made one commit per subdirectory in the repository in order to make it easier to see the changes for a particular subdirectory. To view a particular change, specify that subdirectory as the last parameter on the `git show` or `git diff` commands.
- The `x86-base.inc` file, which is included by all x86-based machine configurations, now sets `IMAGE_FSTYPES` using `+=` to "live" rather than appending with `+=`. This change makes the default easier to override.
- BitBake fires multiple "BuildStarted" events when multiconfig is enabled (one per configuration). For more information, see the "Events" section in the BitBake User Manual.
- By default, the `security_flags.inc` file sets a `GCCPIE` variable with an option to enable Position Independent Executables (PIE) within `gcc`. Enabling PIE in the GNU C Compiler (GCC), makes Return Oriented Programming (ROP) attacks much more difficult to execute.
- OE-Core now provides a `bitbake-layers` plugin that implements a "create-layer" subcommand. The implementation of this subcommand has resulted in the `yocto-layer` script being deprecated and will likely be removed in the next Yocto Project release.
- The `vmdk`, `vdi`, and `qcow2` image file types are now used in conjunction with the "wic" image type through `CONVERSION_CMD`. Consequently, the equivalent image types are now `wic.vmdk`, `wic.vdi`, and `wic.qcow2`, respectively.
- `do_image_<type>[depends]` has replaced `IMAGE_DEPENDS_<type>`. If you have your own classes that implement custom image types, then you need to update them.
- OpenSSL 1.1 has been introduced. However, the default is still 1.0.x through the `PREFERRED_VERSION` variable. This preference is set is due to the remaining compatibility issues with other software. The `PROVIDES` variable in the `openssl 1.0` recipe now includes "openssl10" as a marker that can be used in `DEPENDS` within recipes that build software that still depend on OpenSSL 1.0.

- To ensure consistent behavior, BitBake's "-r" and "-R" options (i.e. prefile and postfile), which are used to read or post-read additional configuration files from the command line, now only affect the current BitBake command. Before these BitBake changes, these options would "stick" for future executions.

## 17.21 Release 2.3 (pyro)

This section provides migration information for moving to the Yocto Project 2.3 Release (codename "pyro") from the prior release.

### 17.21.1 Recipe-specific Sysroots

The OpenEmbedded build system now uses one sysroot per recipe to resolve long-standing issues with configuration script auto-detection of undeclared dependencies. Consequently, you might find that some of your previously written custom recipes are missing declared dependencies, particularly those dependencies that are incidentally built earlier in a typical build process and thus are already likely to be present in the shared sysroot in previous releases.

Consider the following:

- *Declare Build-Time Dependencies:* Because of this new feature, you must explicitly declare all build-time dependencies for your recipe. If you do not declare these dependencies, they are not populated into the sysroot for the recipe.
- *Specify Pre-Installation and Post-Installation Native Tool Dependencies:* You must specifically specify any special native tool dependencies of `pkg_preinst` and `pkg_postinst` scripts by using the `PACKAGE_WRITE_DEPS` variable. Specifying these dependencies ensures that these tools are available if these scripts need to be run on the build host during the `do_rootfs` task.

As an example, see the `dbus` recipe. You will see that this recipe has a `pkg_postinst` that calls `systemctl` if "systemd" is in `DISTRO_FEATURES`. In the example, `systemd-systemctl-native` is added to `PACKAGE_WRITE_DEPS`, which is also conditional on "systemd" being in `DISTRO_FEATURES`.

- *Examine Recipes that Use SSTATEPOSTINSTFUNCS:* You need to examine any recipe that uses `SSTATEPOSTINSTFUNCS` and determine steps to take.

Functions added to `SSTATEPOSTINSTFUNCS` are still called as they were in previous Yocto Project releases. However, since a separate sysroot is now being populated for every recipe and if existing functions being called through `SSTATEPOSTINSTFUNCS` are doing relocation, then you will need to change these to use a post-installation script that is installed by a function added to `SYSROOT_PREPROCESS_FUNCS`.

For an example, see the `pixbufcache` class in `meta/classes/` in the *I Repository del Codice Sorgente di Yocto Project*.

#### Nota

The `SSTATEPOSTINSTFUNCS` variable itself is now deprecated in favor of the `do_populate_sysroot[postfuncs]` task. Consequently, if you do still have any function or functions that need to be called after the sysroot component is created for a recipe, then you would be well advised to take steps to use a post installation script as described previously. Taking these steps prepares your code for when `SSTATEPOSTINSTFUNCS` is removed in a future Yocto Project release.

- *Specify the Sysroot when Using Certain External Scripts:* Because the shared sysroot is now gone, the scripts `oe-find-native-sysroot` and `oe-run-native` have been changed such that you need to specify which recipe's `STAGING_DIR_NATIVE` is used.

#### Nota

You can find more information on how recipe-specific sysroots work in the "*staging*" section.

### 17.21.2 PATH Variable

Within the environment used to run build tasks, the environment variable `PATH` is now sanitized such that the normal native binary paths (`/bin`, `/sbin`, `/usr/bin` and so forth) are removed and a directory containing symbolic links linking only to the binaries from the host mentioned in the `HOSTTOOLS` and `HOSTTOOLS_NONFATAL` variables is added to `PATH`.

Consequently, any native binaries provided by the host that you need to call needs to be in one of these two variables at the configuration level.

Alternatively, you can add a native recipe (i.e. `-native`) that provides the binary to the recipe's `DEPENDS` value.

#### Nota

`PATH` is not sanitized in the same way within `devshell`. If it were, you would have difficulty running host tools for development and debugging within the shell.

### 17.21.3 Changes to Scripts

The following changes to scripts took place:

- `oe-find-native-sysroot`: The usage for the `oe-find-native-sysroot` script has changed to the following:

```
$ . oe-find-native-sysroot recipe
```

You must now supply a recipe for recipe as part of the command. Prior to the Yocto Project 2.3 release, it was not necessary to provide the script with the command.

- `oe-run-native`: The usage for the `oe-run-native` script has changed to the following:

```
$ oe-run-native native_recipe tool
```

You must supply the name of the native recipe and the tool you want to run as part of the command. Prior to the Yocto Project 2.3 release, it was not necessary to provide the native recipe with the command.

- `cleanup-workdir`: The `cleanup-workdir` script has been removed because the script was found to be deleting files it should not have, which lead to broken build trees. Rather than trying to delete portions of `TMPDIR` and getting it wrong, it is recommended that you delete `TMPDIR` and have it restored from shared state (`sstate`) on subsequent builds.

- `wipe-sysroot`: The `wipe-sysroot` script has been removed as it is no longer needed with recipe-specific sysroots.

## 17.21.4 Changes to Functions

The previously deprecated `bb.data.getVar()`, `bb.data.setVar()`, and related functions have been removed in favor of `d.getVar()`, `d.setVar()`, and so forth.

You need to fix any references to these old functions.

## 17.21.5 BitBake Changes

The following changes took place for BitBake:

- *BitBake's Graphical Dependency Explorer UI Replaced*: BitBake's graphical dependency explorer UI `depexp` was replaced by `taskexp` ("Task Explorer"), which provides a graphical way of exploring the `task-depends.dot` file. The data presented by Task Explorer is much more accurate than the data that was presented by `depexp`. Being able to visualize the data is an often requested feature as standard `*.dot` file viewers cannot usual cope with the size of the `task-depends.dot` file.
- *BitBake "-g" Output Changes*: The `package-depends.dot` and `pn-depends.dot` files as previously generated using the `bitbake -g` command have been removed. A `recipe-depends.dot` file is now generated as a collapsed version of `task-depends.dot` instead.

The reason for this change is because `package-depends.dot` and `pn-depends.dot` largely date back to a time before task-based execution and do not take into account task-level dependencies between recipes, which could be misleading.

- *Mirror Variable Splitting Changes*: Mirror variables including `MIRRORS`, `PREMIRRORS`, and `SSTATE_MIRRORS` can now separate values entirely with spaces. Consequently, you no longer need `"\n"`. BitBake looks for pairs of values, which simplifies usage. There should be no change required to existing mirror variable values themselves.
- *The Subversion (SVN) Fetcher Uses an "ssh" Parameter and Not an "rsh" Parameter*: The SVN fetcher now takes an `"ssh"` parameter instead of an `"rsh"` parameter. This new optional parameter is used when the `"protocol"` parameter is set to `"svn+ssh"`. You can only use the new parameter to specify the `ssh` program used by SVN. The SVN fetcher passes the new parameter through the `SVN_SSH` environment variable during the `do_fetch` task.

See the "[Subversion \(SVN\) Fetcher \(svn://\)](#)" section in the BitBake User Manual for additional information.

- `BB_SETSCENE_VERIFY_FUNCTION` and `BB_SETSCENE_VERIFY_FUNCTION2` Removed: Because the mechanism they were part of is no longer necessary with recipe-specific sysroots, the `BB_SETSCENE_VERIFY_FUNCTION` and `BB_SETSCENE_VERIFY_FUNCTION2` variables have been removed.



### 17.21.6 Absolute Symbolic Links

Absolute symbolic links (symlinks) within staged files are no longer permitted and now trigger an error. Any explicit creation of symlinks can use the `lnr` script, which is a replacement for `ln -r`.

If the build scripts in the software that the recipe is building are creating a number of absolute symlinks that need to be corrected, you can inherit `relative_symlinks` within the recipe to turn those absolute symlinks into relative symlinks.

### 17.21.7 GPLv2 Versions of GPLv3 Recipes Moved

Older GPLv2 versions of GPLv3 recipes have moved to a separate `meta-gplv2` layer.

If you use `INCOMPATIBLE_LICENSE` to exclude GPLv3 or set `PREFERRED_VERSION` to substitute a GPLv2 version of a GPLv3 recipe, then you must add the `meta-gplv2` layer to your configuration.

#### Nota

You can find `meta-gplv2` layer in the OpenEmbedded layer index at <https://layers.openembedded.org/layerindex/branch/master/layer/meta-gplv2>.

These relocated GPLv2 recipes do not receive the same level of maintenance as other core recipes. The recipes do not get security fixes and upstream no longer maintains them. In fact, the upstream community is actively hostile towards people that use the old versions of the recipes. Moving these recipes into a separate layer both makes the different needs of the recipes clearer and clearly identifies the number of these recipes.

#### Nota

The long-term solution might be to move to BSD-licensed replacements of the GPLv3 components for those that need to exclude GPLv3-licensed components from the target system. This solution will be investigated for future Yocto Project releases.

### 17.21.8 Package Management Changes

The following package management changes took place:

- Smart package manager is replaced by DNF package manager. Smart has become unmaintained upstream, is not ported to Python 3.x. Consequently, Smart needed to be replaced. DNF is the only feasible candidate.

The change in functionality is that the on-target runtime package management from remote package feeds is now done with a different tool that has a different set of command-line options. If you have scripts that call the tool directly, or use its API, they need to be fixed.

For more information, see the [DNF Documentation](#).

- Rpm 5.x is replaced with Rpm 4.x. This is done for two major reasons:
  - DNF is API-incompatible with Rpm 5.x and porting it and maintaining the port is non-trivial.
  - Rpm 5.x itself has limited maintenance upstream, and the Yocto Project is one of the very few remaining users.

- Berkeley DB 6.x is removed and Berkeley DB 5.x becomes the default:
  - Version 6.x of Berkeley DB has largely been rejected by the open source community due to its AGPLv3 license. As a result, most mainstream open source projects that require DB are still developed and tested with DB 5.x.
  - In OE-core, the only thing that was requiring DB 6.x was Rpm 5.x. Thus, no reason exists to continue carrying DB 6.x in OE-core.
- `createrepo` is replaced with `createrepo_c`.

`createrepo_c` is the current incarnation of the tool that generates remote repository metadata. It is written in C as compared to `createrepo`, which is written in Python. `createrepo_c` is faster and is maintained.
- Architecture-independent RPM packages are "noarch" instead of "all".

This change was made because too many places in DNF/RPM4 stack already make that assumption. Only the filenames and the architecture tag has changed. Nothing else has changed in OE-core system, particularly in the *allarch* class.
- Signing of remote package feeds using `PACKAGE_FEED_SIGN` is not currently supported. This issue will be fully addressed in a future Yocto Project release. See [defect 11209](#) for more information on a solution to package feed signing with RPM in the Yocto Project 2.3 release.
- OPKG now uses the libsolv backend for resolving package dependencies by default. This is vastly superior to OPKG's internal ad-hoc solver that was previously used. This change does have a small impact on disk (around 500 KB) and memory footprint.

**i Nota**

For further details on this change, see the [commit message](#).

## 17.21.9 Removed Recipes

The following recipes have been removed:

- `linux-yocto` 4.8: Version 4.8 has been removed. Versions 4.1 (LTSI), 4.4 (LTS), 4.9 (LTS/LTSI) and 4.10 are now present.
- `python-smartpm`: Functionally replaced by `dnf`.
- `createrepo`: Replaced by the `createrepo-c` recipe.
- `rpmresolve`: No longer needed with the move to RPM 4 as RPM itself is used instead.
- `gststreamer`: Removed the GStreamer Git version recipes as they have been stale. 1.10.x recipes are still present.
- `alsa-conf-base`: Merged into `alsa-conf` since `libasound` depended on both. Essentially, no way existed to install only one of these.
- `tremor`: Moved to `meta-multimedia`. Fixed-integer Vorbis decoding is not needed by current hardware. Thus, GStreamer's `ivorbis` plugin has been disabled by default eliminating the need for the `tremor` recipe in *OpenEmbedded-Core (OE-Core)*.

- `gummiboot`: Replaced by `systemd-boot`.

### 17.21.10 Wic Changes

The following changes have been made to Wic:

#### Nota

For more information on Wic, see the "*Creating Partitioned Images Using Wic*" section in the Yocto Project Development Tasks Manual.

- *Default Output Directory Changed*: Wic's default output directory is now the current directory by default instead of the unusual `/var/tmp/wic`.

The `-o` and `--outdir` options remain unchanged and are used to specify your preferred output directory if you do not want to use the default directory.

- *fsimage Plug-in Removed*: The Wic fsimage plugin has been removed as it duplicates functionality of the rawcopy plugin.

### 17.21.11 QA Changes

The following QA checks have changed:

- `unsafe-references-in-binaries`: The `unsafe-references-in-binaries` QA check, which was disabled by default, has now been removed. This check was intended to detect binaries in `/bin` that link to libraries in `/usr/lib` and have the case where the user has `/usr` on a separate filesystem to `/`.

The removed QA check was buggy. Additionally, `/usr` residing on a separate partition from `/` is now a rare configuration. Consequently, `unsafe-references-in-binaries` was removed.

- `file-rdeps`: The `file-rdeps` QA check is now an error by default instead of a warning. Because it is an error instead of a warning, you need to address missing runtime dependencies.

For additional information, see the *insane* class and the "*Errors and Warnings*" section.

### 17.21.12 Miscellaneous Changes

The following miscellaneous changes have occurred:

- In this release, a number of recipes have been changed to ignore the `largefile` *DISTRO\_FEATURES* item, enabling large file support unconditionally. This feature has always been enabled by default. Disabling the feature has not been widely tested.

#### Nota

Future releases of the Yocto Project will remove entirely the ability to disable the `largefile` feature, which would make it unconditionally enabled everywhere.

- If the *DISTRO\_VERSION* value contains the value of the *DATE* variable, which is the default between Poky releases, the *DATE* value is explicitly excluded from `/etc/issue` and `/etc/issue.net`, which is displayed

at the login prompt, in order to avoid conflicts with Multilib enabled. Regardless, the *DATE* value is inaccurate if the `base-files` recipe is restored from shared state (sstate) rather than rebuilt.

If you need the build date recorded in `/etc/issue*` or anywhere else in your image, a better method is to define a post-processing function to do it and have the function called from *ROOTFS\_POSTPROCESS\_COMMAND*. Doing so ensures the value is always up-to-date with the created image.

- Dropbear's `init` script now disables DSA host keys by default. This change is in line with the systemd service file, which supports RSA keys only, and with recent versions of OpenSSH, which deprecates DSA host keys.
- The *buildhistory* class now correctly uses tabs as separators between all columns in `installed-package-sizes.txt` in order to aid import into other tools.
- The `USE_LDCONFIG` variable has been replaced with the "ldconfig" *DISTRO\_FEATURES* feature. Distributions that previously set:

```
USE_LDCONFIG = "0"
```

should now instead use the following:

```
DISTRO_FEATURES_BACKFILL_CONSIDERED_append = " ldconfig"
```

- The default value of *COPYLEFT\_LICENSE\_INCLUDE* now includes all versions of AGPL licenses in addition to GPL and LGPL.

#### Nota

The default list is not intended to be guaranteed as a complete safe list. You should seek legal advice based on what you are distributing if you are unsure.

- Kernel module packages are now suffixed with the kernel version in order to allow module packages from multiple kernel versions to co-exist on a target system. If you wish to return to the previous naming scheme that does not include the version suffix, use the following:

```
KERNEL_MODULE_PACKAGE_SUFFIX = ""
```

- Removal of `libtool *.la` files is now enabled by default. The `*.la` files are not actually needed on Linux and relocating them is an unnecessary burden.

If you need to preserve these `.la` files (e.g. in a custom distribution), you must change *INHERIT\_DISTRO* such that *"remove-libtool"* is not included in the value.

- Extensible SDKs built for GCC 5+ now refuse to install on a distribution where the host GCC version is 4.8 or 4.9. This change resulted from the fact that the installation is known to fail due to the way the *uninative* shared state (sstate) package is built. See the *uninative* class for additional information.
- All *native* and *nativesdk* recipes now use a separate *DISTRO\_FEATURES* value instead of sharing the value used by recipes for the target, in order to avoid unnecessary rebuilds.

The *DISTRO\_FEATURES* for *native* recipes is *DISTRO\_FEATURES\_NATIVE* added to an intersection of *DISTRO\_FEATURES* and *DISTRO\_FEATURES\_FILTER\_NATIVE*.

For *nativesdk* recipes, the corresponding variables are *DISTRO\_FEATURES\_NATIVESDK* and *DISTRO\_FEATURES\_FILTER\_NATIVESDK*.

- The `FILESDIR` variable, which was previously deprecated and rarely used, has now been removed. You should change any recipes that set `FILESDIR` to set *FILESPATH* instead.
- The `MULTIMACH_HOST_SYS` variable has been removed as it is no longer needed with recipe-specific sysroots.

## 17.22 Release 2.2 (morty)

This section provides migration information for moving to the Yocto Project 2.2 Release (codename "morty") from the prior release.

### 17.22.1 Minimum Kernel Version

The minimum kernel version for the target system and for SDK is now 3.2.0, due to the upgrade to `glibc 2.24`. Specifically, for AArch64-based targets the version is 3.14. For Nios II-based targets, the minimum kernel version is 3.19.

#### Nota

For x86 and x86\_64, you can reset *OLDEST\_KERNEL* to anything down to 2.6.32 if desired.

### 17.22.2 Staging Directories in Sysroot Has Been Simplified

The way directories are staged in sysroot has been simplified and introduces the new *SYSROOT\_DIRS*, *SYSROOT\_DIRS\_NATIVE*, and *SYSROOT\_DIRS\_BLACKLIST* (replaced by *SYSROOT\_DIRS\_IGNORE* in version 4.0). See the [v2 patch series on the OE-Core Mailing List](#) for additional information.

### 17.22.3 Removal of Old Images and Other Files in `tmp/deplo`y Now Enabled

Removal of old images and other files in `tmp/deplo/` is now enabled by default due to a new staging method used for those files. As a result of this change, the `RM_OLD_IMAGE` variable is now redundant.

### 17.22.4 Python Changes

The following changes for Python occurred:

#### BitBake Now Requires Python 3.4+

BitBake requires Python 3.4 or greater.

#### UTF-8 Locale Required on Build Host

A UTF-8 locale is required on the build host due to Python 3. Since C.UTF-8 is not a standard, the default is `en_US.UTF-8`.

## Metadata Must Now Use Python 3 Syntax

The metadata is now required to use Python 3 syntax. For help preparing metadata, see any of the many Python 3 porting guides available. Alternatively, you can reference the conversion commits for BitBake and you can use *OpenEmbedded-Core (OE-Core)* as a guide for changes. Particular areas of interest are:

- subprocess command-line pipes needing locale decoding
- the syntax for octal values changed
- the `iter*()` functions changed name
- iterators now return views, not lists
- changed names for Python modules

## Target Python Recipes Switched to Python 3

Most target Python recipes have now been switched to Python 3. Unfortunately, systems using RPM as a package manager and providing online package-manager support through SMART still require Python 2.

### Nota

Python 2 and recipes that use it can still be built for the target as with previous versions.

## `buildtools-tarball` Includes Python 3

The *buildtools* tarball now includes Python 3.

## 17.22.5 uClibc Replaced by musl

uClibc has been removed in favor of musl. Musl has matured, is better maintained, and is compatible with a wider range of applications as compared to uClibc.

## 17.22.6 `${B}` No Longer Default Working Directory for Tasks

`${B}` is no longer the default working directory for tasks. Consequently, any custom tasks you define now need to either have the `[dirs]` flag set, or the task needs to change into the appropriate working directory manually (e.g using `cd` for a shell task).

### Nota

The preferred method is to use the `[dirs]` flag.

## 17.22.7 `runqemu` Ported to Python

`runqemu` has been ported to Python and has changed behavior in some cases. Previous usage patterns continue to be supported.

The new `runqemu` is a Python script. Machine knowledge is no longer hardcoded into `runqemu`. You can choose to use the `qemuboot` configuration file to define the BSP's own arguments and to make it bootable with `runqemu`. If you use a configuration file, use the following form:

```
image-name-machine.qemuboot.conf
```

The configuration file enables fine-grained tuning of options passed to QEMU without the `runqemu` script hardcoding any knowledge about different machines. Using a configuration file is particularly convenient when trying to use QEMU with machines other than the `qemu*` machines in *OpenEmbedded-Core (OE-Core)*. The `qemuboot.conf` file is generated by the `qemuboot` class when the root filesystem is being built (i.e. build rootfs). QEMU boot arguments can be set in BSP's configuration file and the `qemuboot` class will save them to `qemuboot.conf`.

If you want to use `runqemu` without a configuration file, use the following command form:

```
$ runqemu machine rootfs kernel [options]
```

Supported machines are as follows:

- `qemuarm`
- `qemuarm64`
- `qemux86`
- `qemux86-64`
- `qemuppc`
- `qemumips`
- `qemumips64`
- `qemumipsel`
- `qemumips64el`

Consider the following example, which uses the `qemux86-64` machine, provides a root filesystem, provides an image, and uses the `nographic` option:

```
$ runqemu qemux86-64 tmp/deploy/images/qemux86-64/core-image-minimal-qemux86-64.  
→ext4 tmp/deploy/images/qemux86-64/bzImage nographic
```

Here is a list of variables that can be set in configuration files such as `bsp.conf` to enable the BSP to be booted by `runqemu`:

```
QB_SYSTEM_NAME: QEMU name (e.g. "qemu-system-i386")
QB_OPT_APPEND: Options to append to QEMU (e.g. "-show-cursor")
QB_DEFAULT_KERNEL: Default kernel to boot (e.g. "bzImage")
QB_DEFAULT_FSTYPE: Default FSTYPE to boot (e.g. "ext4")
QB_MEM: Memory (e.g. "-m 512")
QB_MACHINE: QEMU machine (e.g. "-machine virt")
QB_CPU: QEMU cpu (e.g. "-cpu qemu32")
```

(continues on next page)

(continua dalla pagina precedente)

QB\_CPU\_KVM: Similar to QB\_CPU **except** used **for** kvm support (e.g. `"-cpu kvm64"`)

QB\_KERNEL\_CMDLINE\_APPEND: Options to append to the kernel's `-append` option (e.g. `"console=ttyS0 console=tty"`)

QB\_DTB: QEMU dtb name

QB\_AUDIO\_DRV: QEMU audio driver (e.g. `"alsa"`, set it when support audio)

QB\_AUDIO\_OPT: QEMU audio option (e.g. `"-soundhw ac97,es1370"`), which **is** used when QB\_AUDIO\_DRV **is** set.

QB\_KERNEL\_ROOT: Kernel's root (e.g. `/dev/vda`)

QB\_TAP\_OPT: Network option **for** 'tap' mode (e.g. `"-netdev tap,id=net0,ifname=@TAP@,script=no,downscript=no -device virtio-net-device,netdev=net0"`).  
 ↪ runqemu will replace `"@TAP@"` **with** the one that **is** used, such as `tap0, ↪ tap1 ...`

QB\_SLIRP\_OPT: Network option **for** SLIRP mode (e.g. `"-netdev user,id=net0 -device virtio-net-device,netdev=net0"`)

QB\_ROOTFS\_OPT: Used **as** rootfs (e.g. `"-drive id=disk0,file=@ROOTFS@,if=none,format=raw -device virtio-blk-device,drive=disk0"`).  
 ↪ runqemu will replace `"@ROOTFS@"` **with** the one which **is** used, such as `core-image-minimal-qemuarm64.ext4`.

QB\_SERIAL\_OPT: Serial port (e.g. `"-serial mon:stdio"`)

QB\_TCPSERIAL\_OPT: tcp serial port option (e.g. `"-device virtio-serial-device -chardev socket,id=virtcon, ↪ port=@PORT@,host=127.0.0.1 -device virtconsole,chardev=virtcon"`).  
 ↪ runqemu will replace `"@PORT@"` **with** the port number which **is** used.

To use runqemu, set *IMAGE\_CLASSES* as follows and run runqemu:

#### Nota

"QB" means "QEMU Boot".



**i Nota**

For command-line syntax, use `runqemu help`.

```
IMAGE_CLASSES += "qemuboot"
```

### 17.22.8 Default Linker Hash Style Changed

The default linker hash style for `gcc-cross` is now "sysv" in order to catch recipes that are building software without using the OpenEmbedded *LDFLAGS*. This change could result in seeing some "No GNU\_HASH in the elf binary" QA issues when building such recipes. You need to fix these recipes so that they use the expected *LDFLAGS*. Depending on how the software is built, the build system used by the software (e.g. a Makefile) might need to be patched. However, sometimes making this fix is as simple as adding the following to the recipe:

```
TARGET_CC_ARCH += "${LDFLAGS}"
```

### 17.22.9 KERNEL\_IMAGE\_BASE\_NAME no Longer Uses KERNEL\_IMAGETYPE

The `KERNEL_IMAGE_BASE_NAME` variable no longer uses the *KERNEL\_IMAGETYPE* variable to create the image's base name. Because the OpenEmbedded build system can now build multiple kernel image types, this part of the kernel image base name has been removed leaving only the following:

```
KERNEL_IMAGE_BASE_NAME ?= "${PKGE}-${PKGVERSION}-${PKGR}-${MACHINE}-${DATETIME}"
```

If you have recipes or classes that use `KERNEL_IMAGE_BASE_NAME` directly, you might need to update the references to ensure they continue to work.

### 17.22.10 IMGDEPLOYDIR Replaces DEPLOY\_DIR\_IMAGE for Most Use Cases

The *IMGDEPLOYDIR* variable was introduced to allow sstate caching of image creation results. Image recipes defining custom *IMAGE\_CMD* or doing postprocessing on the generated images need to be adapted to use *IMGDEPLOYDIR* instead of *DEPLOY\_DIR\_IMAGE*. *IMAGE\_MANIFEST* creation and symlinking of the most recent image file will fail otherwise.

### 17.22.11 BitBake Changes

The following changes took place for BitBake:

- The "goggle" UI and standalone image-writer tool have been removed as they both require GTK+ 2.0 and were not being maintained.
- The Perforce fetcher now supports *SRCREV* for specifying the source revision to use, be it *AUTOREV*, changelist number, p4date, or label, in preference to separate *SRC\_URI* parameters to specify these. This change is more in-line with how the other fetchers work for source control systems. Recipes that fetch from Perforce will need to be updated to use *SRCREV* in place of specifying the source revision within *SRC\_URI*.
- Some of BitBake's internal code structures for accessing the recipe cache needed to be changed to support the new multi-configuration functionality. These changes will affect external tools that use BitBake's tinfoil module.

For information on these changes, see the changes made to the scripts supplied with OpenEmbedded-Core: 1 and 2.

- The task management code has been rewritten to avoid using ID indirection in order to improve performance. This change is unlikely to cause any problems for most users. However, the setscene verification function as pointed to by `BB_SETSCENE_VERIFY_FUNCTION` needed to change signature. Consequently, a new variable named `BB_SETSCENE_VERIFY_FUNCTION2` has been added allowing multiple versions of BitBake to work with suitably written metadata, which includes OpenEmbedded-Core and Poky. Anyone with custom BitBake task scheduler code might also need to update the code to handle the new structure.

## 17.22.12 Swabber has Been Removed

Swabber, a tool that was intended to detect host contamination in the build process, has been removed, as it has been unmaintained and unused for some time and was never particularly effective. The OpenEmbedded build system has since incorporated a number of mechanisms including enhanced QA checks that mean that there is less of a need for such a tool.

## 17.22.13 Removed Recipes

The following recipes have been removed:

- `augeas`: No longer needed and has been moved to `meta-oe`.
- `directfb`: Unmaintained and has been moved to `meta-oe`.
- `gcc`: Removed 4.9 version. Versions 5.4 and 6.2 are still present.
- `gnome-doc-utils`: No longer needed.
- `gtk-doc-stub`: Replaced by `gtk-doc`.
- `gtk-engines`: No longer needed and has been moved to `meta-gnome`.
- `gtk-sato-engine`: Became obsolete.
- `libglade`: No longer needed and has been moved to `meta-oe`.
- `libmad`: Unmaintained and functionally replaced by `libmpg123`. `libmad` has been moved to `meta-oe`.
- `libowl`: Became obsolete.
- `libxsettings-client`: No longer needed.
- `oh-puzzles`: Functionally replaced by `puzzles`.
- `oprofileui`: Became obsolete. OProfile has been largely supplanted by `perf`.
- `packagegroup-core-directfb.bb`: Removed.
- `core-image-directfb.bb`: Removed.
- `pointercal`: No longer needed and has been moved to `meta-oe`.
- `python-imaging`: No longer needed and moved to `meta-python`.
- `python-pyrex`: No longer needed and moved to `meta-python`.
- `sato-icon-theme`: Became obsolete.

- `swabber-native`: Swabber has been removed. See the [entry on Swabber](#).
- `tslib`: No longer needed and has been moved to `meta-oe`.
- `uclibc`: Removed in favor of `musl`.
- `xtscal`: No longer needed and moved to `meta-oe`

### 17.22.14 Removed Classes

The following classes have been removed:

- `distutils-native-base`: No longer needed.
- `distutils3-native-base`: No longer needed.
- `sdl`: Only set [DEPENDS](#) and [SECTION](#), which are better set within the recipe instead.
- `sip`: Mostly unused.
- `swabber`: See the [entry on Swabber](#).

### 17.22.15 Minor Packaging Changes

The following minor packaging changes have occurred:

- `grub`: Split `grub-editenv` into its own package.
- `systemd`: Split container and vm related units into a new package, `systemd-container`.
- `util-linux`: Moved `prlimit` to a separate `util-linux-prlimit` package.

### 17.22.16 Miscellaneous Changes

The following miscellaneous changes have occurred:

- `package_regex.inc`: Removed because the definitions `package_regex.inc` previously contained have been moved to their respective recipes.
- Both `devtool add` and `recipetool create` now use a fixed [SRCREV](#) by default when fetching from a Git repository. You can override this in either case to use `${AUTOREV}` instead by using the `-a` or `--autorev` command-line option
- `distcc`: GTK+ UI is now disabled by default.
- `packagegroup-core-tools-testapps`: Removed Piglit.
- [image](#): Renamed `COMPRESS(ION)` to `CONVERSION`. This change means that `COMPRESSIONTYPES`, `COMPRESS_DEPENDS` and `COMPRESS_CMD` are deprecated in favor of `CONVERSIONTYPES`, `CONVERSION_DEPENDS` and [CONVERSION\\_CMD](#). The `COMPRESS*` variable names will still work in the 2.2 release but metadata that does not need to be backwards-compatible should be changed to use the new names as the `COMPRESS*` ones will be removed in a future release.
- `gtk-doc`: A full version of `gtk-doc` is now made available. However, some old software might not be capable of using the current version of `gtk-doc` to build documentation. You need to change recipes that build such software so that they explicitly disable building documentation with `gtk-doc`.

## 17.23 Release 2.1 (krogoth)

This section provides migration information for moving to the Yocto Project 2.1 Release (codename "krogoth") from the prior release.

### 17.23.1 Variable Expansion in Python Functions

Variable expressions, such as `${VARNAME}` no longer expand automatically within Python functions. Suppressing expansion was done to allow Python functions to construct shell scripts or other code for situations in which you do not want such expressions expanded. For any existing code that relies on these expansions, you need to change the expansions to expand the value of individual variables through `d.getVar()`. To alternatively expand more complex expressions, use `d.expand()`.

### 17.23.2 Overrides Must Now be Lower-Case

The convention for overrides has always been for them to be lower-case characters. This practice is now a requirement as BitBake's datastore now assumes lower-case characters in order to give a slight performance boost during parsing. In practical terms, this requirement means that anything that ends up in *OVERRIDES* must now appear in lower-case characters (e.g. values for *MACHINE*, *TARGET\_ARCH*, *DISTRO*, and also recipe names if `_pn-recipe` overrides are to be effective).

### 17.23.3 Expand Parameter to `getVar()` and `getVarFlag()` is Now Mandatory

The `expand` parameter to `getVar()` and `getVarFlag()` previously defaulted to `False` if not specified. Now, however, no default exists so one must be specified. You must change any `getVar()` calls that do not specify the final `expand` parameter to calls that do specify the parameter. You can run the following `sed` command at the base of a layer to make this change:

```
sed -e 's:\(\\.getVar([^\,()]*\)):\\1, False):g' -i `grep -ril getVar *`
sed -e 's:\(\\.getVarFlag([^\,()]*,[^\,()]*\)):\\1, False):g' -i `grep -ril getVarFlag`
↪ *
```

#### Nota

The reason for this change is that it prepares the way for changing the default to `True` in a future Yocto Project release. This future change is a much more sensible default than `False`. However, the change needs to be made gradually as a sudden change of the default would potentially cause side-effects that would be difficult to detect.

### 17.23.4 Makefile Environment Changes

*EXTRA\_OEMAKE* now defaults to `""` instead of `"-e MAKEFLAGS="`. Setting *EXTRA\_OEMAKE* to `"-e MAKEFLAGS="` by default was a historical accident that has required many classes (e.g. *autotools\**, *module*) and recipes to override this default in order to work with sensible build systems. When upgrading to the release, you must edit any recipe that relies upon this old default by either setting *EXTRA\_OEMAKE* back to `"-e MAKEFLAGS="` or by explicitly setting any required variable value overrides using *EXTRA\_OEMAKE*, which is typically only needed when

a Makefile sets a default value for a variable that is inappropriate for cross-compilation using the "=" operator rather than the "?=" operator.

### 17.23.5 libexecdir Reverted to \${prefix}/libexec

The use of `${libdir}/${BPN}` as `libexecdir` is different as compared to all other mainstream distributions, which either uses `${prefix}/libexec` or `${libdir}`. The use is also contrary to the GNU Coding Standards (i.e. [https://www.gnu.org/prep/standards/html\\_node/Directory-Variables.html](https://www.gnu.org/prep/standards/html_node/Directory-Variables.html)) that suggest `${prefix}/libexec` and also notes that any package-specific nesting should be done by the package itself. Finally, having `libexecdir` change between recipes makes it very difficult for different recipes to invoke binaries that have been installed into `libexecdir`. The Filesystem Hierarchy Standard (i.e. [https://refspecs.linuxfoundation.org/FHS\\_3.0/fhs/ch04s07.html](https://refspecs.linuxfoundation.org/FHS_3.0/fhs/ch04s07.html)) now recognizes the use of `${prefix}/libexec/`, giving distributions the choice between `${prefix}/lib` or `${prefix}/libexec` without breaking FHS.

### 17.23.6 ac\_cv\_sizeof\_off\_t is No Longer Cached in Site Files

For recipes inheriting the *autotools\** class, `ac_cv_sizeof_off_t` is no longer cached in the site files for `autoconf`. The reason for this change is because the `ac_cv_sizeof_off_t` value is not necessarily static per architecture as was previously assumed. Rather, the value changes based on whether large file support is enabled. For most software that uses `autoconf`, this change should not be a problem. However, if you have a recipe that bypasses the standard *do\_configure* task from the *autotools\** class and the software the recipe is building uses a very old version of `autoconf`, the recipe might be incapable of determining the correct size of `off_t` during *do\_configure*.

The best course of action is to patch the software as necessary to allow the default implementation from the *autotools\** class to work such that `autoreconf` succeeds and produces a working configure script, and to remove the overridden *do\_configure* task such that the default implementation does get used.

### 17.23.7 Image Generation is Now Split Out from Filesystem Generation

Previously, for image recipes the *do\_rootfs* task assembled the filesystem and then from that filesystem generated images. With this Yocto Project release, image generation is split into separate *do\_image* tasks for clarity both in operation and in the code.

For most cases, this change does not present any problems. However, if you have made customizations that directly modify the *do\_rootfs* task or that mention *do\_rootfs*, you might need to update those changes. In particular, if you had added any tasks after *do\_rootfs*, you should make edits so that those tasks are after the *do\_image\_complete* task rather than after *do\_rootfs* so that your added tasks run at the correct time.

A minor part of this restructuring is that the post-processing definitions and functions have been moved from the *image* class to the *rootfs-postcommands* class. Functionally, however, they remain unchanged.

### 17.23.8 Removed Recipes

The following recipes have been removed in the 2.1 release:

- `gcc` version 4.8: Versions 4.9 and 5.3 remain.
- `qt4`: All support for Qt 4.x has been moved out to a separate `meta-qt4` layer because Qt 4 is no longer supported upstream.

- `x11vnc`: Moved to the `meta-oe` layer.
- `linux-yocto-3.14`: No longer supported.
- `linux-yocto-3.19`: No longer supported.
- `libjpeg`: Replaced by the `libjpeg-turbo` recipe.
- `pth`: Became obsolete.
- `liboil`: Recipe is no longer needed and has been moved to the `meta-multimedia` layer.
- `gtk-theme-torturer`: Recipe is no longer needed and has been moved to the `meta-gnome` layer.
- `gnome-mime-data`: Recipe is no longer needed and has been moved to the `meta-gnome` layer.
- `udev`: Replaced by the `eudev` recipe for compatibility when using `sysvinit` with newer kernels.
- `python-pygtk`: Recipe became obsolete.
- `adt-installer`: Recipe became obsolete. See the "[ADT Removed](#)" section for more information.

### 17.23.9 Class Changes

The following classes have changed:

- `autotools_stage`: Removed because the [autotools\\*](#) class now provides its functionality. Recipes that inherited from `autotools_stage` should now inherit from [autotools\\*](#) instead.
- `boot-directdisk`: Merged into the `image-vm` class. The `boot-directdisk` class was rarely directly used. Consequently, this change should not cause any issues.
- `bootimg`: Merged into the [image-live](#) class. The `bootimg` class was rarely directly used. Consequently, this change should not cause any issues.
- `packageinfo`: Removed due to its limited use by the Hob UI, which has itself been removed.

### 17.23.10 Build System User Interface Changes

The following changes have been made to the build system user interface:

- *Hob GTK+-based UI*: Removed because it is unmaintained and based on the outdated GTK+ 2 library. The Toaster web-based UI is much more capable and is actively maintained. See the "[Utilizzo dell'Interfaccia Web di Toaster](#)" section in the Toaster User Manual for more information on this interface.
- *"puccho" BitBake UI*: Removed because is unmaintained and no longer useful.

### 17.23.11 ADT Removed

The Application Development Toolkit (ADT) has been removed because its functionality almost completely overlapped with the [standard SDK](#) and the [extensible SDK](#). For information on these SDKs and how to build and use them, see the [Manuale di Sviluppo di Applicazioni Yocto Project e Software Development Kit \(SDK/eSDK\)](#) manual.

**i Nota**

The Yocto Project Eclipse IDE Plug-in is still supported and is not affected by this change.

### 17.23.12 Poky Reference Distribution Changes

The following changes have been made for the Poky distribution:

- The `meta-yocto` layer has been renamed to `meta-poky` to better match its purpose, which is to provide the Poky reference distribution. The `meta-yocto-bsp` layer retains its original name since it provides reference machines for the Yocto Project and it is otherwise unrelated to Poky. References to `meta-yocto` in your `build/conf/bblayers.conf` should automatically be updated, so you should not need to change anything unless you are relying on this naming elsewhere.
- The `uninative` class is now enabled by default in Poky. This class attempts to isolate the build system from the host distribution's C library and makes re-use of native shared state artifacts across different host distributions practical. With this class enabled, a tarball containing a pre-built C library is downloaded at the start of the build.

The `uninative` class is enabled through the `meta/conf/distro/include/yocto-uninative.inc` file, which for those not using the Poky distribution, can include to easily enable the same functionality.

Alternatively, if you wish to build your own `uninative` tarball, you can do so by building the `uninative-tarball` recipe, making it available to your build machines (e.g. over HTTP/HTTPS) and setting a similar configuration as the one set by `yocto-uninative.inc`.

- Static library generation, for most cases, is now disabled by default in the Poky distribution. Disabling this generation saves some build time as well as the size used for build output artifacts.

Disabling this library generation is accomplished through a `meta/conf/distro/include/no-static-libs.inc`, which for those not using the Poky distribution can easily include to enable the same functionality.

Any recipe that needs to opt-out of having the `--disable-static` option specified on the `configure` command line either because it is not a supported option for the `configure` script or because static libraries are needed should set the following variable:

```
DISABLE_STATIC = ""
```

- The separate `poky-tiny` distribution now uses the musl C library instead of a heavily pared down `glibc`. Using musl results in a smaller distribution and facilitates much greater maintainability because musl is designed to have a small footprint.

If you have used `poky-tiny` and have customized the `glibc` configuration you will need to redo those customizations with musl when upgrading to the new release.

### 17.23.13 Packaging Changes

The following changes have been made to packaging:

- The `runuser` and `mountpoint` binaries, which were previously in the main `util-linux` package, have been split out into the `util-linux-runuser` and `util-linux-mountpoint` packages, respectively.
- The `python-elementtree` package has been merged into the `python-xml` package.

### 17.23.14 Tuning File Changes

The following changes have been made to the tuning files:

- The "no-thumb-interwork" tuning feature has been dropped from the ARM tune include files. Because interworking is required for ARM EABI, attempting to disable it through a tuning feature no longer makes sense.

#### Nota

Support for ARM OABI was deprecated in gcc 4.7.

- The `tune-cortexm*.inc` and `tune-cortexr4.inc` files have been removed because they are poorly tested. Until the OpenEmbedded build system officially gains support for CPUs without an MMU, these tuning files would probably be better maintained in a separate layer if needed.

### 17.23.15 Supporting GObject Introspection

This release supports generation of GLib Introspective Repository (GIR) files through GObject introspection, which is the standard mechanism for accessing GObject-based software from runtime environments. You can enable, disable, and test the generation of this data. See the "[Enabling GObject Introspection Support](#)" section in the Yocto Project Development Tasks Manual for more information.

### 17.23.16 Miscellaneous Changes

These additional changes exist:

- The minimum Git version has been increased to 1.8.3.1. If your host distribution does not provide a sufficiently recent version, you can install the [buildtools](#), which will provide it. See the [Versioni richieste di Git, tar, Python, make e gcc](#) section for more information on the [buildtools](#) tarball.
- The buggy and incomplete support for the RPM version 4 package manager has been removed. The well-tested and maintained support for RPM version 5 remains.
- Previously, the following list of packages were removed if package-management was not in [IMA-GE\\_FEATURES](#), regardless of any dependencies:

```
update-rc.d
base-passwd
shadow
```

(continues on next page)



(continua dalla pagina precedente)

```
update-alternatives
run-postinsts
```

With the Yocto Project 2.1 release, these packages are only removed if "read-only-rootfs" is in *IMAGE\_FEATURES*, since they might still be needed for a read-write image even in the absence of a package manager (e.g. if users need to be added, modified, or removed at runtime).

- The *devtool modify* command now defaults to extracting the source since that is most commonly expected. The *-x* or *--extract* options are now no-ops. If you wish to provide your own existing source tree, you will now need to specify either the *-n* or *--no-extract* options when running `devtool modify`.
- If the formfactor for a machine is either not supplied or does not specify whether a keyboard is attached, then the default is to assume a keyboard is attached rather than assume no keyboard. This change primarily affects the Sato UI.
- The *.debug* directory packaging is now automatic. If your recipe builds software that installs binaries into directories other than the standard ones, you no longer need to take care of setting `FILES_${PN}-dbg` to pick up the resulting *.debug* directories as these directories are automatically found and added.
- Inaccurate disk and CPU percentage data has been dropped from *buildstats* output. This data has been replaced with `getrusage()` data and corrected IO statistics. You will probably need to update any custom code that reads the *buildstats* data.
- The `meta/conf/distro/include/package_regex.inc` is now deprecated. The contents of this file have been moved to individual recipes.

#### Nota

Because this file will likely be removed in a future Yocto Project release, it is suggested that you remove any references to the file that might be in your configuration.

- The *v86d/uvesafb* has been removed from the *genericx86* and *genericx86-64* reference machines, which are provided by the *meta-yocto-bsp* layer. Most modern x86 boards do not rely on this file and it only adds kernel error messages during startup. If you do still need to support *uvesafb*, you can simply add *v86d* to your image.
- Build sysroot paths are now removed from debug symbol files. Removing these paths means that remote GDB using an unstripped build system sysroot will no longer work (although this was never documented to work). The supported method to accomplish something similar is to set `IMAGE_GEN_DEBUGFS` to "1", which will generate a companion debug image containing unstripped binaries and associated debug sources alongside the image.

## 17.24 Release 2.0 (jethro)

This section provides migration information for moving to the Yocto Project 2.0 Release (codename "jethro") from the prior release.

### 17.24.1 GCC 5

The default compiler is now GCC 5.2. This change has required fixes for compilation errors in a number of other recipes.

One important example is a fix for when the Linux kernel freezes at boot time on ARM when built with GCC 5. If you are using your own kernel recipe or source tree and building for ARM, you will likely need to apply this [patch](#). The standard `linux-yocto` kernel source tree already has a workaround for the same issue.

For further details, see <https://gcc.gnu.org/gcc-5/changes.html> and the porting guide at [https://gcc.gnu.org/gcc-5/porting\\_to.html](https://gcc.gnu.org/gcc-5/porting_to.html).

Alternatively, you can switch back to GCC 4.9 or 4.8 by setting `GCCVERSION` in your configuration, as follows:

```
GCCVERSION = "4.9%"
```

### 17.24.2 Gstreamer 0.10 Removed

Gstreamer 0.10 has been removed in favor of Gstreamer 1.x. As part of the change, recipes for Gstreamer 0.10 and related software are now located in `meta-multimedia`. This change results in Qt4 having Phonon and Gstreamer support in QtWebkit disabled by default.

### 17.24.3 Removed Recipes

The following recipes have been moved or removed:

- `bluez4`: The recipe is obsolete and has been moved due to `bluez5` becoming fully integrated. The `bluez4` recipe now resides in `meta-oe`.
- `gamin`: The recipe is obsolete and has been removed.
- `gnome-icon-theme`: The recipe's functionality has been replaced by `adwaita-icon-theme`.
- `Gstreamer 0.10 Recipes`: Recipes for Gstreamer 0.10 have been removed in favor of the recipes for Gstreamer 1.x.
- `insserv`: The recipe is obsolete and has been removed.
- `libunique`: The recipe is no longer used and has been moved to `meta-oe`.
- `midori`: The recipe's functionality has been replaced by `epiphany`.
- `python-gst`: The recipe is obsolete and has been removed since it only contains bindings for Gstreamer 0.10.
- `qt-mobility`: The recipe is obsolete and has been removed since it requires Gstreamer 0.10, which has been replaced.
- `subversion`: All 1.6.x versions of this recipe have been removed.
- `webkit-gtk`: The older 1.8.3 version of this recipe has been removed in favor of `webkitgtk`.

### 17.24.4 BitBake datastore improvements

The method by which BitBake's datastore handles overrides has changed. Overrides are now applied dynamically and `bb.data.update_data()` is now a no-op. Thus, `bb.data.update_data()` is no longer required in order to apply the correct overrides. In practice, this change is unlikely to require any changes to Metadata. However, these minor changes in behavior exist:

- All potential overrides are now visible in the variable history as seen when you run the following:

```
$ bitbake -e
```

- `d.delVar('VARNAME')` and `d.setVar('VARNAME', None)` result in the variable and all of its overrides being cleared out. Before the change, only the non-overridden values were cleared.

### 17.24.5 Shell Message Function Changes

The shell versions of the BitBake message functions (i.e. `bbdebug`, `bbnote`, `bbwarn`, `bbplain`, `bberror`, and `bbfatal`) are now connected through to their BitBake equivalents `bb.debug()`, `bb.note()`, `bb.warn()`, `bb.plain()`, `bb.error()`, and `bb.fatal()`, respectively. Thus, those message functions that you would expect to be printed by the BitBake UI are now actually printed. In practice, this change means two things:

- If you now see messages on the console that you did not previously see as a result of this change, you might need to clean up the calls to `bbwarn`, `bberror`, and so forth. Or, you might want to simply remove the calls.
- The `bbfatal` message function now suppresses the full error log in the UI, which means any calls to `bbfatal` where you still wish to see the full error log should be replaced by `die` or `bbfatal_log`.

### 17.24.6 Extra Development/Debug Package Cleanup

The following recipes have had extra `dev/dbg` packages removed:

- `acl`
- `apmd`
- `aspell`
- `attr`
- `augeas`
- `bzip2`
- `cogl`
- `curl`
- `elfutils`
- `gcc-target`
- `libgcc`
- `libtool`
- `libxmu`

- `opkg`
- `pciutils`
- `rpm`
- `sysfsutils`
- `tiff`
- `xz`

All of the above recipes now conform to the standard packaging scheme where a single `-dev`, `-dbg`, and `-staticdev` package exists per recipe.

### 17.24.7 Recipe Maintenance Tracking Data Moved to OE-Core

Maintenance tracking data for recipes that was previously part of `meta-yocto` has been moved to *OpenEmbedded-Core (OE-Core)*. The change includes `package_regex.inc` and `distro_alias.inc`, which are typically enabled when using the `distrodata` class. Additionally, the contents of `upstream_tracking.inc` has now been split out to the relevant recipes.

### 17.24.8 Automatic Stale Sysroot File Cleanup

Stale files from recipes that no longer exist in the current configuration are now automatically removed from sysroot as well as removed from any other place managed by shared state. This automatic cleanup means that the build system now properly handles situations such as renaming the build system side of recipes, removal of layers from *build/conf/bblayers.conf*, and *DISTRO\_FEATURES* changes.

Additionally, work directories for old versions of recipes are now pruned. If you wish to disable pruning old work directories, you can set the following variable in your configuration:

```
SSTATE_PRUNE_OBSOLETEWORKDIR = "0"
```

### 17.24.9 linux-yocto Kernel Metadata Repository Now Split from Source

The `linux-yocto` tree has up to now been a combined set of kernel changes and configuration (meta) data carried in a single tree. While this format is effective at keeping kernel configuration and source modifications synchronized, it is not always obvious to developers how to manipulate the Metadata as compared to the source.

Metadata processing has now been removed from the *kernel-yocto* class and the external Metadata repository `yocto-kernel-cache`, which has always been used to seed the `linux-yocto` "meta" branch. This separate `linux-yocto` cache repository is now the primary location for this data. Due to this change, `linux-yocto` is no longer able to process combined trees. Thus, if you need to have your own combined kernel repository, you must do the split there as well and update your recipes accordingly. See the `meta/recipes-kernel/linux/linux-yocto_4.1.bb` recipe for an example.

## 17.24.10 Additional QA checks

The following QA checks have been added:

- Added a "host-user-contaminated" check for ownership issues for packaged files outside of `/home`. The check looks for files that are incorrectly owned by the user that ran BitBake instead of owned by a valid user in the target system.
- Added an "invalid-chars" check for invalid (non-UTF8) characters in recipe metadata variable values (i.e. `DESCRIPTION`, `SUMMARY`, `LICENSE`, and `SECTION`). Some package managers do not support these characters.
- Added an "invalid-packageconfig" check for any options specified in `PACKAGECONFIG` that do not match any `PACKAGECONFIG` option defined for the recipe.

## 17.24.11 Miscellaneous Changes

These additional changes exist:

- `gtk-update-icon-cache` has been renamed to `gtk-icon-utils`.
- The tools-profile `IMAGE_FEATURES` item as well as its corresponding packagegroup and package-group-core-tools-profile no longer bring in `oprofile`. Bringing in `oprofile` was originally added to aid compilation on resource-constrained targets. However, this aid has not been widely used and is not likely to be used going forward due to the more powerful target platforms and the existence of better cross-compilation tools.
- The `IMAGE_FSTYPES` variable's default value now specifies `ext4` instead of `ext3`.
- All support for the `PRINC` variable has been removed.
- The packagegroup-core-full-cmdline packagegroup no longer brings in `lighttpd` due to the fact that bringing in `lighttpd` is not really in line with the packagegroup's purpose, which is to add full versions of command-line tools that by default are provided by `busybox`.

## 17.25 Release 1.8 (fido)

This section provides migration information for moving to the Yocto Project 1.8 Release (codename "fido") from the prior release.

### 17.25.1 Removed Recipes

The following recipes have been removed:

- `owl-video`: Functionality replaced by `gst-player`.
- `gaku`: Functionality replaced by `gst-player`.
- `gnome-desktop`: This recipe is now available in `meta-gnome` and is no longer needed.
- `gsettings-desktop-schemas`: This recipe is now available in `meta-gnome` and is no longer needed.
- `python-argparse`: The `argparse` module is already provided in the default Python distribution in a package named `python-argparse`. Consequently, the separate `python-argparse` recipe is no longer needed.

- `telepathy-python`, `libtelepathy`, `telepathy-glib`, `telepathy-idle`, `telepathy-mission-control`: All these recipes have moved to `meta-oe` and are consequently no longer needed by any recipes in `OpenEmbedded-Core`.
- `linux-yocto_3.10` and `linux-yocto_3.17`: Support for the `linux-yocto` 3.10 and 3.17 kernels has been dropped. Support for the 3.14 kernel remains, while support for 3.19 kernel has been added.
- `poky-feed-config-opkg`: This recipe has become obsolete and is no longer needed. Use `distro-feed-config` from `meta-oe` instead.
- `libav 0.8.x`: `libav 9.x` is now used.
- `sed-native`: No longer needed. A working version of `sed` is expected to be provided by the host distribution.

### 17.25.2 BlueZ 4.x / 5.x Selection

Proper built-in support for selecting BlueZ 5.x in preference to the default of 4.x now exists. To use BlueZ 5.x, simply add "bluez5" to your `DISTRO_FEATURES` value. If you had previously added append files (`*.bbappend`) to make this selection, you can now remove them.

Additionally, a `bluetooth` class has been added to make selection of the appropriate bluetooth support within a recipe a little easier. If you wish to make use of this class in a recipe, add something such as the following:

```
inherit bluetooth
PACKAGECONFIG ??= "${@bb.utils.contains('DISTRO_FEATURES', 'bluetooth', '${BLUEZ}',
↪  '', d)}"
PACKAGECONFIG[bluez4] = "--enable-bluetooth,--disable-bluetooth,bluez4"
PACKAGECONFIG[bluez5] = "--enable-bluez5,--disable-bluez5,bluez5"
```

### 17.25.3 Kernel Build Changes

The kernel build process was changed to place the source in a common shared work area and to place build artifacts separately in the source code tree. In theory, migration paths have been provided for most common usages in kernel recipes but this might not work in all cases. In particular, users need to ensure that `${S}` (source files) and `${B}` (build artifacts) are used correctly in functions such as `do_configure` and `do_install`. For kernel recipes that do not inherit from `kernel-yocto` or include `linux-yocto.inc`, you might wish to refer to the `linux.inc` file in the `meta-oe` layer for the kinds of changes you need to make. For reference, here is the [commit](#) where the `linux.inc` file in `meta-oe` was updated.

Recipes that rely on the kernel source code and do not inherit the `module` classes might need to add explicit dependencies on the `do_shared_workdir` kernel task, for example:

```
do_configure[depends] += "virtual/kernel:do_shared_workdir"
```

### 17.25.4 SSL 3.0 is Now Disabled in OpenSSL

SSL 3.0 is now disabled when building OpenSSL. Disabling SSL 3.0 avoids any lingering instances of the POODLE vulnerability. If you feel you must re-enable SSL 3.0, then you can add an append file (`*.bbappend`) for the `openssl` recipe to remove "-no-ssl3" from `EXTRA_OECONF`.

## 17.25.5 Default Sysroot Poisoning

`gcc's` default sysroot and include directories are now "poisoned". In other words, the sysroot and include directories are being redirected to a non-existent location in order to catch when host directories are being used due to the correct options not being passed. This poisoning applies both to the cross-compiler used within the build and to the cross-compiler produced in the SDK.

If this change causes something in the build to fail, it almost certainly means the various compiler flags and commands are not being passed correctly to the underlying piece of software. In such cases, you need to take corrective steps.

## 17.25.6 Rebuild Improvements

Changes have been made to the *base*, *autotools\**, and *cmake* classes to clean out generated files when the *do\_configure* task needs to be re-executed.

One of the improvements is to attempt to run "make clean" during the *do\_configure* task if a `Makefile` exists. Some software packages do not provide a working clean target within their make files. If you have such recipes, you need to set *CLEANBROKEN* to "1" within the recipe, for example:

```
CLEANBROKEN = "1"
```

## 17.25.7 QA Check and Validation Changes

The following QA Check and Validation Changes have occurred:

- Usage of `PRINC` previously triggered a warning. It now triggers an error. You should remove any remaining usage of `PRINC` in any recipe or append file.
- An additional QA check has been added to detect usage of `${D}` in *FILES* values where *D* values should not be used at all. The same check ensures that `$D` is used in `pkg_preinst/pkg_postinst/pkg_prerm/pkg_postrm` functions instead of `${D}`.
- *S* now needs to be set to a valid value within a recipe. If *S* is not set in the recipe, the directory is not automatically created. If *S* does not point to a directory that exists at the time the *do\_unpack* task finishes, a warning will be shown.
- *LICENSE* is now validated for correct formatting of multiple licenses. If the format is invalid (e.g. multiple licenses are specified with no operators to specify how the multiple licenses interact), then a warning will be shown.

## 17.25.8 Miscellaneous Changes

The following miscellaneous changes have occurred:

- The `send-error-report` script now expects a "-s" option to be specified before the server address. This assumes a server address is being specified.
- The `oe-pkgdata-util` script now expects a "-p" option to be specified before the `pkgdata` directory, which is now optional. If the `pkgdata` directory is not specified, the script will run BitBake to query *PKGDATA\_DIR* from the build environment.

## 17.26 Release 1.7 (dizzy)

This section provides migration information for moving to the Yocto Project 1.7 Release (codename "dizzy") from the prior release.

### 17.26.1 Changes to Setting QEMU `PACKAGECONFIG` Options in `local.conf`

The QEMU recipe now uses a number of `PACKAGECONFIG` options to enable various optional features. The method used to set defaults for these options means that existing `build/conf/local.conf` files will need to be modified to append to `PACKAGECONFIG` for `qemu-native` and `nativesdk-qemu` instead of setting it. In other words, to enable graphical output for QEMU, you should now have these lines in `build/conf/local.conf`:

```
PACKAGECONFIG_append_pn-qemu-native = " sdl"
PACKAGECONFIG_append_pn-nativesdk-qemu = " sdl"
```

### 17.26.2 Minimum Git version

The minimum `Git` version required on the build host is now 1.7.8 because the `--list` option is now required by BitBake's Git fetcher. As always, if your host distribution does not provide a version of Git that meets this requirement, you can use the `buildtools` tarball that does. See the "*Versioni richieste di Git, tar, Python, make e gcc*" section for more information.

### 17.26.3 Autotools Class Changes

The following `autotools*` class changes occurred:

- *A separate `.term:Build Directory` is now used by default:* The `autotools*` class has been changed to use a directory for building (`B`), which is separate from the source directory (`S`). This is commonly referred to as `B != S`, or an out-of-tree build.

If the software being built is already capable of building in a directory separate from the source, you do not need to do anything. However, if the software is not capable of being built in this manner, you will need to either patch the software so that it can build separately, or you will need to change the recipe to inherit the `autotools-brokensep` class instead of the `autotools*` or `autotools_stage` classes.

- *The `--foreign` option is no longer passed to `automake` when running `autoconf`:* This option tells `automake` that a particular software package does not follow the GNU standards and therefore should not be expected to distribute certain files such as `ChangeLog`, `AUTHORS`, and so forth. Because the majority of upstream software packages already tell `automake` to enable foreign mode themselves, the option is mostly superfluous. However, some recipes will need patches for this change. You can easily make the change by patching `configure.ac` so that it passes "foreign" to `AM_INIT_AUTOMAKE()`. See [this commit](#) for an example showing how to make the patch.



## 17.26.4 Binary Configuration Scripts Disabled

Some of the core recipes that package binary configuration scripts now disable the scripts due to the scripts previously requiring error-prone path substitution. Software that links against these libraries using these scripts should use the much more robust `pkg-config` instead. The list of recipes changed in this version (and their configuration scripts) is as follows:

```
directfb (directfb-config)
freetype (freetype-config)
gpgme (gpgme-config)
libassuan (libassuan-config)
libcroco (croco-6.0-config)
libgcrypt (libgcrypt-config)
libgpg-error (gpg-error-config)
libksba (ksba-config)
libpcap (pcap-config)
libpcre (pcre-config)
libpng (libpng-config, libpng16-config)
libsdl (sdl-config)
libusb-compat (libusb-config)
libxml2 (xml2-config)
libxslt (xslt-config)
ncurses (ncurses-config)
neon (neon-config)
npth (npth-config)
pth (pth-config)
taglib (taglib-config)
```

Additionally, support for `pkg-config` has been added to some recipes in the previous list in the rare cases where the upstream software package does not already provide it.

## 17.26.5 `eglibc 2.19` Replaced with `glibc 2.20`

Because `eglibc` and `glibc` were already fairly close, this replacement should not require any significant changes to other software that links to `eglibc`. However, there were a number of minor changes in `glibc 2.20` upstream that could require patching some software (e.g. the removal of the `_BSD_SOURCE` feature test macro).

`glibc 2.20` requires version 2.6.32 or greater of the Linux kernel. Thus, older kernels will no longer be usable in conjunction with it.

For full details on the changes in `glibc 2.20`, see the upstream release notes [here](#).

## 17.26.6 Kernel Module Autoloading

The `module_autoload_*` variable is now deprecated and a new `KERNEL_MODULE_AUTOLOAD` variable should be used instead. Also, `module_conf_*` must now be used in conjunction with a new `KERNEL_MODULE_PROBECONF` variable. The new variables no longer require you to specify the module name as part of the variable name. This change not only simplifies usage but also allows the values of these variables to be appropriately incorporated into

task signatures and thus trigger the appropriate tasks to re-execute when changed. You should replace any references to `module_autoload_*` with `KERNEL_MODULE_AUTOLOAD`, and add any modules for which `module_conf_*` is specified to `KERNEL_MODULE_PROBECONF`.

## 17.26.7 QA Check Changes

The following changes have occurred to the QA check process:

- Additional QA checks `file-rdeps` and `build-deps` have been added in order to verify that file dependencies are satisfied (e.g. package contains a script requiring `/bin/bash`) and build-time dependencies are declared, respectively. For more information, please see the "[QA Error and Warning Messages](#)" chapter.
- Package QA checks are now performed during a new `do_package_qa` task rather than being part of the `do_package` task. This allows more parallel execution. This change is unlikely to be an issue except for highly customized recipes that disable packaging tasks themselves by marking them as `noexec`. For those packages, you will need to disable the `do_package_qa` task as well.
- Files being overwritten during the `do_populate_sysroot` task now trigger an error instead of a warning. Recipes should not be overwriting files written to the sysroot by other recipes. If you have these types of recipes, you need to alter them so that they do not overwrite these files.

You might now receive this error after changes in configuration or metadata resulting in orphaned files being left in the sysroot. If you do receive this error, the way to resolve the issue is to delete your `TMPDIR` or to move it out of the way and then re-start the build. Anything that has been fully built up to that point and does not need rebuilding will be restored from the shared state cache and the rest of the build will be able to proceed as normal.

## 17.26.8 Removed Recipes

The following recipes have been removed:

- `x-load`: This recipe has been superseded by U-Boot SPL for all Cortex-based TI SoCs. For legacy boards, the `meta-ti` layer, which contains a maintained recipe, should be used instead.
- `ubootchart`: This recipe is obsolete. A `bootchart2` recipe has been added to functionally replace it.
- `linux-yocto 3.4`: Support for the linux-yocto 3.4 kernel has been dropped. Support for the 3.10 and 3.14 kernels remains, while support for version 3.17 has been added.
- `eglibc` has been removed in favor of `glibc`. See the "[eglibc 2.19 Replaced with glibc 2.20](#)" section for more information.

## 17.26.9 Miscellaneous Changes

The following miscellaneous change occurred:

- The build history feature now writes `build-id.txt` instead of `build-id`. Additionally, `build-id.txt` now contains the full build header as printed by BitBake upon starting the build. You should manually remove old "build-id" files from your existing build history repositories to avoid confusion. For information on the build history feature, see the "[Maintaining Build Output Quality with buildhistory](#)" section in the Yocto Project Development Tasks Manual.

## 17.27 Release 1.6 (daisy)

This section provides migration information for moving to the Yocto Project 1.6 Release (codename "daisy") from the prior release.

### 17.27.1 archiver Class

The *archiver* class has been rewritten and its configuration has been simplified. For more details on the source archiver, see the "*Maintaining Open Source License Compliance During Your Product's Lifecycle*" section in the Yocto Project Development Tasks Manual.

### 17.27.2 Packaging Changes

The following packaging changes have been made:

- The `binutils` recipe no longer produces a `binutils-symlinks` package. `update-alternatives` is now used to handle the preferred `binutils` variant on the target instead.
- The `tc` (traffic control) utilities have been split out of the main `iproute2` package and put into the `iproute2-tc` package.
- The `gtk-engines` schemas have been moved to a dedicated `gtk-engines-schemas` package.
- The `armv7a` with thumb package architecture suffix has changed. The suffix for these packages with the thumb optimization enabled is "t2" as it should be. Use of this suffix was not the case in the 1.5 release. Architecture names will change within package feeds as a result.

### 17.27.3 BitBake

The following changes have been made to *BitBake*.

#### Matching Branch Requirement for Git Fetching

When fetching source from a Git repository using *SRC\_URI*, BitBake will now validate the *SRCREV* value against the branch. You can specify the branch using the following form:

```
SRC_URI = "git://server.name/repository;branch=branchname"
```

If you do not specify a branch, BitBake looks in the default "master" branch.

Alternatively, if you need to bypass this check (e.g. if you are fetching a revision corresponding to a tag that is not on any branch), you can add ";nobranch=1" to the end of the URL within *SRC\_URI*.

#### Python Definition substitutions

BitBake had some previously deprecated Python definitions within its `bb` module removed. You should use their sub-module counterparts instead:

- `bb.MalformedUrl`: Use `bb.fetch.MalformedUrl`.
- `bb.encodeurl`: Use `bb.fetch.encodeurl`.
- `bb.decodeurl`: Use `bb.fetch.decodeurl`.

- `bb.mkdirhier`: Use `bb.utils.mkdirhier`.
- `bb.movefile`: Use `bb.utils.movefile`.
- `bb.copyfile`: Use `bb.utils.copyfile`.
- `bb.which`: Use `bb.utils.which`.
- `bb.vercmp_string`: Use `bb.utils.vercmp_string`.
- `bb.vercmp`: Use `bb.utils.vercmp`.

## SVK Fetcher

The SVK fetcher has been removed from BitBake.

## Console Output Error Redirection

The BitBake console UI will now output errors to `stderr` instead of `stdout`. Consequently, if you are piping or redirecting the output of `bitbake` to somewhere else, and you wish to retain the errors, you will need to add `2>&1` (or something similar) to the end of your `bitbake` command line.

## task-taskname Overrides

`task-taskname` overrides have been adjusted so that tasks whose names contain underscores have the underscores replaced by hyphens for the override so that they now function properly. For example, the task override for `do_populate_sdk` is `task-populate-sdk`.

## 17.27.4 Changes to Variables

The following variables have changed. For information on the OpenEmbedded build system variables, see the "*Glossario delle Variabili*" Chapter.

### TMPDIR

`TMPDIR` can no longer be on an NFS mount. NFS does not offer full POSIX locking and inode consistency and can cause unexpected issues if used to store `TMPDIR`.

The check for this occurs on startup. If `TMPDIR` is detected on an NFS mount, an error occurs.

### PRINC

The `PRINC` variable has been deprecated and triggers a warning if detected during a build. For `PR` increments on changes, use the PR service instead. You can find out more about this service in the "*Working With a PR Service*" section in the Yocto Project Development Tasks Manual.

### IMAGE\_TYPES

The "sum.jffs2" option for `IMAGE_TYPES` has been replaced by the "jffs2.sum" option, which fits the processing order.

### **COPY\_LIC\_MANIFEST**

The *COPY\_LIC\_MANIFEST* variable must now be set to "1" rather than any value in order to enable it.

### **COPY\_LIC\_DIRS**

The *COPY\_LIC\_DIRS* variable must now be set to "1" rather than any value in order to enable it.

### **PACKAGE\_GROUP**

The *PACKAGE\_GROUP* variable has been renamed to *FEATURE\_PACKAGES* to more accurately reflect its purpose. You can still use *PACKAGE\_GROUP* but the OpenEmbedded build system produces a warning message when it encounters the variable.

## **Preprocess and Post Process Command Variable Behavior**

The following variables now expect a semicolon separated list of functions to call and not arbitrary shell commands:

- *ROOTFS\_PREPROCESS\_COMMAND*
- *ROOTFS\_POSTPROCESS\_COMMAND*
- *SDK\_POSTPROCESS\_COMMAND*
- *POPULATE\_SDK\_POST\_TARGET\_COMMAND*
- *POPULATE\_SDK\_POST\_HOST\_COMMAND*
- *IMAGE\_POSTPROCESS\_COMMAND*
- *IMAGE\_PREPROCESS\_COMMAND*
- *ROOTFS\_POSTUNINSTALL\_COMMAND*
- *ROOTFS\_POSTINSTALL\_COMMAND*

For migration purposes, you can simply wrap shell commands in a shell function and then call the function. Here is an example:

```
my_postprocess_function() {  
    echo "hello" > ${IMAGE_ROOTFS}/hello.txt  
}  
ROOTFS_POSTPROCESS_COMMAND += "my_postprocess_function; "
```

## **17.27.5 Package Test (ptest)**

Package Tests (ptest) are built but not installed by default. For information on using Package Tests, see the "*Testing Packages With ptest*" section in the Yocto Project Development Tasks Manual. See also the "*ptest*" section.

## 17.27.6 Build Changes

Separate build and source directories have been enabled by default for selected recipes where it is known to work and for all recipes that inherit the *cmake* class. In future releases the *autotools\** class will enable a separate *Build Directory* by default as well. Recipes building Autotools-based software that fails to build with a separate *Build Directory* should be changed to inherit from the *autotools-brokensep* class instead of the *autotools\** or *autotools\_stage* classes.

## 17.27.7 qemu-native

*qemu-native* now builds without SDL-based graphical output support by default. The following additional lines are needed in your *build/conf/local.conf* to enable it:

```
PACKAGECONFIG_pn-qemu-native = "sdl"  
ASSUME_PROVIDED += "libsdl-native"
```

### Nota

The default *build/conf/local.conf* contains these statements. Consequently, if you are building a headless system and using a default *build/conf/local.conf* file, you will need comment these two lines out.

## 17.27.8 core-image-basic

*core-image-basic* has been renamed to *core-image-full-cmdline*.

In addition to *core-image-basic* being renamed, *packagegroup-core-basic* has been renamed to *packagegroup-core-full-cmdline* to match.

## 17.27.9 Licenze

The top-level *LICENSE* file has been changed to better describe the license of the various components of *OpenEmbedded-Core (OE-Core)*. However, the licensing itself remains unchanged.

Normally, this change would not cause any side-effects. However, some recipes point to this file within *LIC\_FILES\_CHKSUM* (as `${COREBASE}/LICENSE`) and thus the accompanying checksum must be changed from `3f40d7994397109285ec7b81fdeb3b58` to `4d92cd373abda3937c2bc47fbc49d690`. A better alternative is to have *LIC\_FILES\_CHKSUM* point to a file describing the license that is distributed with the source that the recipe is building, if possible, rather than pointing to `${COREBASE}/LICENSE`.

## 17.27.10 CFLAGS Options

The "-fpermissive" option has been removed from the default *CFLAGS* value. You need to take action on individual recipes that fail when building with this option. You need to either patch the recipes to fix the issues reported by the compiler, or you need to add "-fpermissive" to *CFLAGS* in the recipes.

### 17.27.11 Custom Image Output Types

Custom image output types, as selected using `IMAGE_FSTYPES`, must declare their dependencies on other image types (if any) using a new `IMAGE_TYPEDEP` variable.

### 17.27.12 I Task

The `do_package_write` task has been removed. The task is no longer needed.

### 17.27.13 `update-alternative` Provider

The default `update-alternatives` provider has been changed from `opkg` to `opkg-utils`. This change resolves some troublesome circular dependencies. The runtime package has also been renamed from `update-alternatives-cworth` to `update-alternatives-opkg`.

### 17.27.14 `virtclass` Overrides

The `virtclass` overrides are now deprecated. Use the equivalent class overrides instead (e.g. `virtclass-native` becomes `class-native`.)

### 17.27.15 Removed and Renamed Recipes

The following recipes have been removed:

- `packagegroup-toolset-native` --- this recipe is largely unused.
- `linux-yocto-3.8` --- support for the Linux yocto 3.8 kernel has been dropped. Support for the 3.10 and 3.14 kernels have been added with the `linux-yocto-3.10` and `linux-yocto-3.14` recipes.
- `ocf-linux` --- this recipe has been functionally replaced using `cryptodev-linux`.
- `genext2fs` --- `genext2fs` is no longer used by the build system and is unmaintained upstream.
- `js` --- this provided an ancient version of Mozilla's javascript engine that is no longer needed.
- `zaurusd` --- the recipe has been moved to the `meta-handheld` layer.
- `eglibc 2.17` --- replaced by the `eglibc 2.19` recipe.
- `gcc 4.7.2` --- replaced by the now stable `gcc 4.8.2`.
- `external-sourcery-toolchain` --- this recipe is now maintained in the `meta-sourcery` layer.
- `linux-libc-headers-yocto 3.4+git` --- now using version 3.10 of the `linux-libc-headers` by default.
- `meta-toolchain-gmae` --- this recipe is obsolete.
- `packagegroup-core-sdk-gmae` --- this recipe is obsolete.
- `packagegroup-core-standalone-gmae-sdk-target` --- this recipe is obsolete.

## 17.27.16 Removed Classes

The following classes have become obsolete and have been removed:

- `module_strip`
- `pkg_metainfo`
- `pkg_distribute`
- `image-empty`

## 17.27.17 Reference Board Support Packages (BSPs)

The following reference BSPs changes occurred:

- The BeagleBoard (`beagleboard`) ARM reference hardware has been replaced by the BeagleBone (`beaglebone`) hardware.
- The RouterStation Pro (`routerstationpro`) MIPS reference hardware has been replaced by the EdgeRouter Lite (`edgerouter`) hardware.

The previous reference BSPs for the `beagleboard` and `routerstationpro` machines are still available in a new `meta-yocto-bsp-old` layer in the [Source Repositories](https://git.yoctoproject.org/meta-yocto-bsp-old/) at <https://git.yoctoproject.org/meta-yocto-bsp-old/>.

## 17.28 Release 1.5 (dora)

This section provides migration information for moving to the Yocto Project 1.5 Release (codename "dora") from the prior release.

### 17.28.1 Host Dependency Changes

The OpenEmbedded build system now has some additional requirements on the host system:

- Python 2.7.3+
- Tar 1.24+
- Git 1.7.8+
- Patched version of Make if you are using 3.82. Most distributions that provide Make 3.82 use the patched version.

If the Linux distribution you are using on your build host does not provide packages for these, you can install and use the Buildtools tarball, which provides an SDK-like environment containing them.

For more information on this requirement, see the "*Versioni richieste di Git, tar, Python, make e gcc*" section.

### 17.28.2 `atom-pc` Board Support Package (BSP)

The `atom-pc` hardware reference BSP has been replaced by a `genericx86` BSP. This BSP is not necessarily guaranteed to work on all x86 hardware, but it will run on a wider range of systems than the `atom-pc` did.



**i Nota**

Additionally, a `genericx86-64` BSP has been added for 64-bit Atom systems.

### 17.28.3 BitBake

The following changes have been made that relate to BitBake:

- BitBake now supports a `_remove` operator. The addition of this operator means you will have to rename any items in recipe space (functions, variables) whose names currently contain `_remove_` or end with `_remove` to avoid unexpected behavior.
- BitBake's global method pool has been removed. This method is not particularly useful and led to clashes between recipes containing functions that had the same name.
- The "none" server backend has been removed. The "process" server backend has been serving well as the default for a long time now.
- The `bitbake-runtask` script has been removed.
- `${P}` and `${PF}` are no longer added to *PROVIDES* by default in `bitbake.conf`. These version-specific *PROVIDES* items were seldom used. Attempting to use them could result in two versions being built simultaneously rather than just one version due to the way BitBake resolves dependencies.

### 17.28.4 QA Warnings

The following changes have been made to the package QA checks:

- If you have customized *ERROR\_QA* or *WARN\_QA* values in your configuration, check that they contain all of the issues that you wish to be reported. Previous Yocto Project versions contained a bug that meant that any item not mentioned in *ERROR\_QA* or *WARN\_QA* would be treated as a warning. Consequently, several important items were not already in the default value of *WARN\_QA*. All of the possible QA checks are now documented in the "*insane*" section.
- An additional QA check has been added to check if `/usr/share/info/dir` is being installed. Your recipe should delete this file within *do\_install* if "make install" is installing it.
- If you are using the *buildhistory* class, the check for the package version going backwards is now controlled using a standard QA check. Thus, if you have customized your *ERROR\_QA* or *WARN\_QA* values and still wish to have this check performed, you should add "version-going-backwards" to your value for one or the other variables depending on how you wish it to be handled. See the documented QA checks in the "*insane*" section.

### 17.28.5 Directory Layout Changes

The following directory changes exist:

- Output SDK installer files are now named to include the image name and tuning architecture through the *SDK\_NAME* variable.
- Images and related files are now installed into a directory that is specific to the machine, instead of a parent directory containing output files for multiple machines. The *DEPLOY\_DIR\_IMAGE* variable continues to point to the directory containing images for the current *MACHINE* and should be used anywhere there is a need to

refer to this directory. The `runqemu` script now uses this variable to find images and kernel binaries and will use BitBake to determine the directory. Alternatively, you can set the `DEPLOY_DIR_IMAGE` variable in the external environment.

- When `buildhistory` is enabled, its output is now written under the *Build Directory* rather than `TMPDIR`. Doing so makes it easier to delete `TMPDIR` and preserve the build history. Additionally, data for produced SDKs is now split by `IMAGE_NAME`.
- When *buildhistory* is enabled, its output is now written under the *Build Directory* rather than `TMPDIR`. Doing so makes it easier to delete `TMPDIR` and preserve the build history. Additionally, data for produced SDKs is now split by `IMAGE_NAME`.
- The `pkgdata` directory produced as part of the packaging process has been collapsed into a single machine-specific directory. This directory is located under `sysroots` and uses a machine-specific name (i.e. `tmp/sysroots/machine/pkgdata`).

### 17.28.6 Shortened Git SRCREV Values

BitBake will now shorten revisions from Git repositories from the normal 40 characters down to 10 characters within *SRCPV* for improved usability in path and filenames. This change should be safe within contexts where these revisions are used because the chances of spatially close collisions is very low. Distant collisions are not a major issue in the way the values are used.

### 17.28.7 IMAGE\_FEATURES

The following changes have been made that relate to *IMAGE\_FEATURES*:

- The value of *IMAGE\_FEATURES* is now validated to ensure invalid feature items are not added. Some users mistakenly add package names to this variable instead of using *IMAGE\_INSTALL* in order to have the package added to the image, which does not work. This change is intended to catch those kinds of situations. Valid *IMAGE\_FEATURES* are drawn from `PACKAGE_GROUP` definitions, *COMPLEMENTARY\_GLOB* and a new "validitems" varflag on *IMAGE\_FEATURES*. The "validitems" varflag change allows additional features to be added if they are not provided using the previous two mechanisms.
- The previously deprecated "apps-console-core" *IMAGE\_FEATURES* item is no longer supported. Add "splash" to *IMAGE\_FEATURES* if you wish to have the splash screen enabled, since this is all that apps-console-core was doing.

### 17.28.8 /run

The `/run` directory from the Filesystem Hierarchy Standard 3.0 has been introduced. You can find some of the implications for this change [here](#). The change also means that recipes that install files to `/var/run` must be changed. You can find a guide on how to make these changes [here](#).

### 17.28.9 Removal of Package Manager Database Within Image Recipes

The `image core-image-minimal` no longer adds `remove_packaging_data_files` to *ROOTFS\_POSTPROCESS\_COMMAND*. This addition is now handled automatically when "package-management" is not in *IMAGE\_FEATURES*. If you have custom image recipes that make this addition, you should remove the lines, as they are not needed and might interfere with correct operation of postinstall scripts.

## 17.28.10 Images Now Rebuild Only on Changes Instead of Every Time

The *do\_rootfs* and other related image construction tasks are no longer marked as "nostamp". Consequently, they will only be re-executed when their inputs have changed. Previous versions of the OpenEmbedded build system always rebuilt the image when requested rather than when necessary.

## 17.28.11 Task Recipes

The previously deprecated `task.bbclass` has now been dropped. For recipes that previously inherited from this class, you should rename them from `task-*` to `packagegroup-*` and inherit *packagegroup* instead.

For more information, see the "*packagegroup*" section.

## 17.28.12 BusyBox

By default, we now split BusyBox into two binaries: one that is `suid root` for those components that need it, and another for the rest of the components. Splitting BusyBox allows for optimization that eliminates the *tinylogin* recipe as recommended by upstream. You can disable this split by setting *BUSYBOX\_SPLIT\_SUID* to "0".

## 17.28.13 Automated Image Testing

A new automated image testing framework has been added through the *testimage* classes. This framework replaces the older *imagetest-qemu* framework.

You can learn more about performing automated image tests in the "*Performing Automated Runtime Testing*" section in the Yocto Project Test Environment Manual.

## 17.28.14 Build History

The changes to Build History are:

- Installed package sizes: *installed-package-sizes.txt* for an image now records the size of the files installed by each package instead of the size of each compressed package archive file.
- The dependency graphs (*depends\*.dot*) now use the actual package names instead of replacing dashes, dots and plus signs with underscores.
- The *buildhistory-diff* and *buildhistory-collect-screvs* utilities have improved command-line handling. Use the `--help` option for each utility for more information on the new syntax.

For more information on Build History, see the "*Maintaining Build Output Quality with buildhistory*" section in the Yocto Project Development Tasks Manual.

## 17.28.15 udev

The changes to *udev* are:

- *udev* no longer brings in *udev-extraconf* automatically through *RRECOMMENDS*, since this was originally intended to be optional. If you need the extra rules, then add *udev-extraconf* to your image.
- *udev* no longer brings in *pciutils-ids* or *usbutils-ids* through *RRECOMMENDS*. These are not needed by *udev* itself and removing them saves around 350KB.

## 17.28.16 Removed and Renamed Recipes

- The `linux-yocto 3.2` kernel has been removed.
- `libtool-nativesdk` has been renamed to `nativesdk-libtool`.
- `tinylogin` has been removed. It has been replaced by a suid portion of Busybox. See the "*BusyBox*" section for more information.
- `external-python-tarball` has been renamed to `buildtools-tarball`.
- `web-webkit` has been removed. It has been functionally replaced by `midori`.
- `imake` has been removed. It is no longer needed by any other recipe.
- `transfig-native` has been removed. It is no longer needed by any other recipe.
- `anjuta-remote-run` has been removed. Anjuta IDE integration has not been officially supported for several releases.

## 17.28.17 Other Changes

Here is a list of short entries describing other changes:

- `run-postinsts`: Make this generic.
- `base-files`: Remove the unnecessary `media/xxx` directories.
- `alsa-state`: Provide an empty `asound.conf` by default.
- `classes/image`: Ensure *BAD\_RECOMMENDATIONS* supports pre-renamed package names.
- `classes/rootfs_rpm`: Implement *BAD\_RECOMMENDATIONS* for RPM.
- `systemd`: Remove `systemd_unitdir` if `systemd` is not in *DISTRO\_FEATURES*.
- `systemd`: Remove `init.d` dir if `systemd` unit file is present and `sysvinit` is not a distro feature.
- `libpam`: Deny all services for the `OTHER` entries.
- *image*: Move `runtime_mapping_rename` to avoid conflict with `multilib`. See [YOCTO #4993](#) in Bugzilla for more information.
- `linux-dtb`: Use kernel build system to generate the `dtb` files.
- `kern-tools`: Switch from `guilt` to new `kgit-s2q` tool.

## 17.29 Release 1.4 (dylan)

This section provides migration information for moving to the Yocto Project 1.4 Release (codename "dylan") from the prior release.

## 17.29.1 BitBake

Differences include the following:

- *Comment Continuation:* If a comment ends with a line continuation (`\`) character, then the next line must also be a comment. Any instance where this is not the case, now triggers a warning. You must either remove the continuation character, or be sure the next line is a comment.
- *Package Name Overrides:* The runtime package specific variables `RDEPENDS`, `RRECOMMENDS`, `RSUGGESTS`, `RPROVIDES`, `RCONFLICTS`, `RREPLACES`, `FILES`, `ALLOW_EMPTY`, and the `pre`, `post`, `install`, and `uninstall` script functions `pkg_preinst`, `pkg_postinst`, `pkg_prerm`, and `pkg_postrm` should always have a package name override. For example, use `RDEPENDS_${PN}` for the main package instead of `RDEPENDS`. BitBake uses more strict checks when it parses recipes.

## 17.29.2 Build Behavior

Differences include the following:

- *Shared State Code:* The shared state code has been optimized to avoid running unnecessary tasks. For example, the following no longer populates the target `sysroot` since that is not necessary:

```
$ bitbake -c rootfs some-image
```

Instead, the system just needs to extract the output package contents, re-create the packages, and construct the root filesystem. This change is unlikely to cause any problems unless you have missing declared dependencies.

- *Scanning Directory Names:* When scanning for files in `SRC_URI`, the build system now uses `FILESOVERRIDES` instead of `OVERRIDES` for the directory names. In general, the values previously in `OVERRIDES` are now in `FILESOVERRIDES` as well. However, if you relied upon an additional value you previously added to `OVERRIDES`, you might now need to add it to `FILESOVERRIDES` unless you are already adding it through the `MACHINEOVERRIDES` or `DISTROOVERRIDES` variables, as appropriate. For more related changes, see the "*Variables*" section.

## 17.29.3 Proxies and Fetching Source

A new `oe-git-proxy` script has been added to replace previous methods of handling proxies and fetching source from Git. See the `meta-yocto/conf/site.conf.sample` file for information on how to use this script.

## 17.29.4 Custom Interfaces File (netbase change)

If you have created your own custom `etc/network/interfaces` file by creating an append file for the `netbase` recipe, you now need to create an append file for the `init-ifupdown` recipe instead, which you can find in *OpenEmbedded-Core (OE-Core)* at `meta/recipes-core/init-ifupdown`. For information on how to use append files, see the "*Appending Other Layers Metadata With Your Layer*" section in the Yocto Project Development Tasks Manual.

## 17.29.5 Remote Debugging

Support for remote debugging with the Eclipse IDE is now separated into an image feature (`eclipse-debug`) that corresponds to the `packagegroup-core-eclipse-debug` package group. Previously, the debugging feature was included through the `tools-debug` image feature, which corresponds to the `packagegroup-core-tools-debug` package group.

## 17.29.6 Variables

The following variables have changed:

- `SANITY_TESTED_DISTROS`: This variable now uses a distribution ID, which is composed of the host distributor ID followed by the release. Previously, `SANITY_TESTED_DISTROS` was composed of the description field. For example, "Ubuntu 12.10" becomes "Ubuntu-12.10". You do not need to worry about this change if you are not specifically setting this variable, or if you are specifically setting it to "".
- `SRC_URI`: The `${PN}`, `${PF}`, `${P}`, and `FILE_DIRNAME` directories have been dropped from the default value of the `FILESPATH` variable, which is used as the search path for finding files referred to in `SRC_URI`. If you have a recipe that relied upon these directories, which would be unusual, then you will need to add the appropriate paths within the recipe or, alternatively, rearrange the files. The most common locations are still covered by `${BP}`, `${BPN}`, and "files", which all remain in the default value of `FILESPATH`.

## 17.29.7 Target Package Management with RPM

If runtime package management is enabled and the RPM backend is selected, Smart is now installed for package download, dependency resolution, and upgrades instead of Zypper. For more information on how to use Smart, run the following command on the target:

```
smart --help
```

## 17.29.8 Recipes Moved

The following recipes were moved from their previous locations because they are no longer used by anything in the OpenEmbedded-Core:

- `clutter-box2d`: Now resides in the `meta-oe` layer.
- `evolution-data-server`: Now resides in the `meta-gnome` layer.
- `gthumb`: Now resides in the `meta-gnome` layer.
- `gtkhtml2`: Now resides in the `meta-oe` layer.
- `gupnp`: Now resides in the `meta-multimedia` layer.
- `gypsy`: Now resides in the `meta-oe` layer.
- `libcanberra`: Now resides in the `meta-gnome` layer.
- `libgdata`: Now resides in the `meta-gnome` layer.
- `libmusicbrainz`: Now resides in the `meta-multimedia` layer.
- `metacity`: Now resides in the `meta-gnome` layer.

- `polkit`: Now resides in the `meta-oe` layer.
- `zeroconf`: Now resides in the `meta-networking` layer.

## 17.29.9 Removals and Renames

The following list shows what has been removed or renamed:

- `evieext`: Removed because it has been removed from `xserver` since 2008.
- `Gtk+ DirectFB`: Removed support because upstream `Gtk+` no longer supports it as of version 2.18.
- `libxfontcache` / `xfontcacheprot`: Removed because they were removed from the Xorg server in 2008.
- `libxp` / `libxprintapputil` / `libxprintutil` / `printproto`: Removed because the XPrint server was removed from Xorg in 2008.
- `libxtrap` / `xtrapproto`: Removed because their functionality was broken upstream.
- *linux-yocto 3.0 kernel*: Removed with `linux-yocto 3.8` kernel being added. The `linux-yocto 3.2` and `linux-yocto 3.4` kernels remain as part of the release.
- `lsbsetup`: Removed with functionality now provided by `lsbtest`.
- `matchbox-stroke`: Removed because it was never more than a proof-of-concept.
- `matchbox-wm-2` / `matchbox-theme-sato-2`: Removed because they are not maintained. However, `matchbox-wm` and `matchbox-theme-sato` are still provided.
- `mesa-dri`: Renamed to `mesa`.
- `mesa-xlib`: Removed because it was no longer useful.
- `mutter`: Removed because nothing ever uses it and the recipe is very old.
- `orinoco-conf`: Removed because it has become obsolete.
- `update-modules`: Removed because it is no longer used. The kernel module `postinstall` and `postrm` scripts can now do the same task without the use of this script.
- `web`: Removed because it is not maintained. Superseded by `web-webkit`.
- `xf86bigfontproto`: Removed because upstream it has been disabled by default since 2007. Nothing uses `xf86bigfontproto`.
- `xf86rushproto`: Removed because its dependency in `xserver` was spurious and it was removed in 2005.
- `zypper` / `libzypp` / `sat-solver`: Removed and been functionally replaced with `Smart (python-smartpm)` when `RPM` packaging is used and package management is enabled on the target.

## 17.30 Release 1.3 (danny)

This section provides migration information for moving to the Yocto Project 1.3 Release (codename "danny") from the prior release.

### 17.30.1 Local Configuration

Differences include changes for *SSTATE\_MIRRORS* and *build/conf/bblayers.conf*.

#### SSTATE\_MIRRORS

The shared state cache (sstate-cache), as pointed to by *SSTATE\_DIR*, by default now has two-character subdirectories to prevent issues arising from too many files in the same directory. Also, native sstate-cache packages, which are built to run on the host system, will go into a subdirectory named using the distro ID string. If you copy the newly structured sstate-cache to a mirror location (either local or remote) and then point to it in *SSTATE\_MIRRORS*, you need to append "PATH" to the end of the mirror URL so that the path used by BitBake before the mirror substitution is appended to the path used to access the mirror. Here is an example:

```
SSTATE_MIRRORS = "file://.* http://someserver.tld/share/sstate/PATH"
```

#### bblayers.conf

The meta-yocto layer consists of two parts that correspond to the Poky reference distribution and the reference hardware Board Support Packages (BSPs), respectively: meta-yocto and meta-yocto-bsp. When running BitBake for the first time after upgrading, your *build/conf/bblayers.conf* file will be updated to handle this change and you will be asked to re-run or restart for the changes to take effect.

### 17.30.2 Ricette

Differences include changes for the following:

#### Python Function Whitespace

All Python functions must now use four spaces for indentation. Previously, an inconsistent mix of spaces and tabs existed, which made extending these functions using `_append` or `_prepend` complicated given that Python treats white-space as syntactically significant. If you are defining or extending any Python functions (e.g. `populate_packages`, `do_unpack`, `do_patch` and so forth) in custom recipes or classes, you need to ensure you are using consistent four-space indentation.

#### proto= in SRC\_URI

Any use of `proto=` in *SRC\_URI* needs to be changed to `protocol=`. In particular, this applies to the following URIs:

- `svn://`
- `hg://`
- `osc://`

Other URIs were already using `protocol=`. This change improves consistency.



## nativesdk

The suffix `nativesdk` is now implemented as a prefix, which simplifies a lot of the packaging code for *nativesdk* recipes. All custom *nativesdk* recipes, which are relocatable packages that are native to *SDK\_ARCH*, and any references need to be updated to use `nativesdk-*` instead of `*-nativesdk`.

## Task Recipes

"Task" recipes are now known as "Package groups" and have been renamed from `task-*.bb` to `packagegroup-*.bb`. Existing references to the previous `task-*` names should work in most cases as there is an automatic upgrade path for most packages. However, you should update references in your own recipes and configurations as they could be removed in future releases. You should also rename any custom `task-*` recipes to `packagegroup-*`, and change them to inherit *packagegroup* instead of *task*, as well as taking the opportunity to remove anything now handled by *packagegroup*, such as providing `-dev` and `-dbg` packages, setting *LIC\_FILES\_CHKSUM*, and so forth. See the *packagegroup* section for further details.

## IMAGE\_FEATURES

Image recipes that previously included `apps-console-core` in *IMAGE\_FEATURES* should now include `splash` instead to enable the boot-up splash screen. Retaining `apps-console-core` will still include the splash screen but generates a warning. The `apps-x11-core` and `apps-x11-games` *IMAGE\_FEATURES* features have been removed.

## Removed Recipes

The following recipes have been removed. For most of them, it is unlikely that you would have any references to them in your own *Metadata*. However, you should check your metadata against this list to be sure:

- `libx11-trim`: Replaced by `libx11`, which has a negligible size difference with modern Xorg.
- `xserver-xorg-lite`: Use `xserver-xorg`, which has a negligible size difference when DRI and GLX modules are not installed.
- `xserver-kdrive`: Effectively unmaintained for many years.
- `mesa-xlib`: No longer serves any purpose.
- `galago`: Replaced by `telepathy`.
- `gail`: Functionality was integrated into GTK+ 2.13.
- `eggdbus`: No longer needed.
- `gcc-*-intermediate`: The build has been restructured to avoid the need for this step.
- `libgsmd`: Unmaintained for many years. Functionality now provided by `ofono` instead.
- *contacts, dates, tasks, eds-tools*: Largely unmaintained PIM application suite. It has been moved to `meta-gnome` in `meta-openembedded`.

In addition to the previously listed changes, the `meta-demoapps` directory has also been removed because the recipes in it were not being maintained and many had become obsolete or broken. Additionally, these recipes were not parsed in the default configuration. Many of these recipes are already provided in an updated and maintained form within the OpenEmbedded community layers such as `meta-oe` and `meta-gnome`. For the remainder, you can now find them in the `meta-extras` repository, which is in the [Source Repositories](https://git.yoctoproject.org/meta-extras/) at <https://git.yoctoproject.org/meta-extras/>.

### 17.30.3 Linux Kernel Naming

The naming scheme for kernel output binaries has been changed to now include *PE* as part of the filename:

```
KERNEL_IMAGE_BASE_NAME ?= "${KERNEL_IMAGETYPE}-${PE}-${PV}-${PR}-${MACHINE}-${DATETIME}"
```

Because the *PE* variable is not set by default, these binary files could result with names that include two dash characters. Here is an example:

```
bzImage--3.10.9+git0+cd502a8814_7144bcc4b8-r0-qemux86-64-20130830085431.bin
```

The Yocto Project ®

<docs@lists.yoctoproject.org>

È consentito copiare, distribuire e/o modificare questo documento secondo i termini della licenza [Creative Commons Attribution-Share Alike 2.0 UK: England & Wales](#) pubblicata da Creative Commons.

Per segnalare eventuali inesattezze o problemi con questo manuale (o con qualsiasi altro manuale di Yocto Project), o per inviare aggiunte o modifiche, si prega di inviare un'e-mail/patch alla mailing list della documentazione di Yocto Project all'indirizzo [docs@lists.yoctoproject.org](mailto:docs@lists.yoctoproject.org) o di accedere su [Libera Chat](#) al canale #yocto.

---

## Supported Release Manuals

---

### 18.1 Release Series 6.0 (wrynose)

- [6.0 Documentation](#)
- [6.0.1 Documentation](#)
- [6.0.2 Documentation](#)
- [6.0.3 Documentation](#)

### 18.2 Release Series 5.0 (scarthgap)

- [5.0 Documentation](#)
- [5.0.1 Documentation](#)
- [5.0.2 Documentation](#)
- [5.0.3 Documentation](#)
- [5.0.4 Documentation](#)
- [5.0.5 Documentation](#)
- [5.0.6 Documentation](#)
- [5.0.7 Documentation](#)
- [5.0.8 Documentation](#)
- [5.0.9 Documentation](#)
- [5.0.10 Documentation](#)

- [5.0.11 Documentation](#)
- [5.0.12 Documentation](#)
- [5.0.13 Documentation](#)
- [5.0.14 Documentation](#)
- [5.0.15 Documentation](#)
- [5.0.16 Documentation](#)
- [5.0.17 Documentation](#)
- [5.0.18 Documentation](#)
- [5.0.19 Documentation](#)
- [5.0.20 Documentation](#)

### 19.1 Release Series 5.3 (whinlatter)

- [5.3 Documentation](#)
- [5.3.1 Documentation](#)
- [5.3.2 Documentation](#)
- [5.3.3 Documentation](#)
- [5.3.4 Documentation](#)

### 19.2 Release Series 5.2 (walnascar)

- [5.2 Documentation](#)
- [5.2.1 Documentation](#)
- [5.2.2 Documentation](#)
- [5.2.3 Documentation](#)
- [5.2.4 Documentation](#)

### 19.3 Release Series 5.1 (styhead)

- [5.1 Documentation](#)
- [5.1.1 Documentation](#)
- [5.1.2 Documentation](#)
- [5.1.3 Documentation](#)

- [5.1.4 Documentation](#)

## 19.4 Release Series 4.3 (nanbield)

- [4.3 Documentation](#)
- [4.3.1 Documentation](#)
- [4.3.2 Documentation](#)
- [4.3.3 Documentation](#)
- [4.3.4 Documentation](#)

## 19.5 Release Series 4.2 (mickledore)

- [4.2 Documentation](#)
- [4.2.1 Documentation](#)
- [4.2.2 Documentation](#)
- [4.2.3 Documentation](#)
- [4.2.4 Documentation](#)

## 19.6 Release Series 4.1 (langdale)

- [4.1 Documentation](#)
- [4.1.1 Documentation](#)
- [4.1.2 Documentation](#)
- [4.1.3 Documentation](#)
- [4.1.4 Documentation](#)

## 19.7 Release Series 4.0 (kirkstone)

- [4.0 Documentation](#)
- [4.0.1 Documentation](#)
- [4.0.2 Documentation](#)
- [4.0.3 Documentation](#)
- [4.0.4 Documentation](#)
- [4.0.5 Documentation](#)
- [4.0.6 Documentation](#)
- [4.0.7 Documentation](#)

- 4.0.8 Documentation
- 4.0.9 Documentation
- 4.0.10 Documentation
- 4.0.11 Documentation
- 4.0.12 Documentation
- 4.0.13 Documentation
- 4.0.14 Documentation
- 4.0.15 Documentation
- 4.0.16 Documentation
- 4.0.17 Documentation
- 4.0.18 Documentation
- 4.0.19 Documentation
- 4.0.20 Documentation
- 4.0.21 Documentation
- 4.0.22 Documentation
- 4.0.23 Documentation
- 4.0.24 Documentation
- 4.0.25 Documentation
- 4.0.26 Documentation
- 4.0.27 Documentation
- 4.0.28 Documentation
- 4.0.29 Documentation
- 4.0.30 Documentation
- 4.0.31 Documentation
- 4.0.32 Documentation
- 4.0.33 Documentation
- 4.0.34 Documentation
- 4.0.35 Documentation

## 19.8 Release Series 3.4 (honister)

- 3.4 Documentation
- 3.4.1 Documentation

- [3.4.2 Documentation](#)
- [3.4.3 Documentation](#)
- [3.4.4 Documentation](#)

## 19.9 Release Series 3.3 (hardknott)

- [3.3 Documentation](#)
- [3.3.1 Documentation](#)
- [3.3.2 Documentation](#)
- [3.3.3 Documentation](#)
- [3.3.4 Documentation](#)
- [3.3.5 Documentation](#)
- [3.3.6 Documentation](#)

## 19.10 Release Series 3.2 (gatesgarth)

- [3.2 Documentation](#)
- [3.2.1 Documentation](#)
- [3.2.2 Documentation](#)
- [3.2.3 Documentation](#)
- [3.2.4 Documentation](#)

## 19.11 Release Series 3.1 (dunfell)

- [3.1 Documentation](#)
- [3.1.1 Documentation](#)
- [3.1.2 Documentation](#)
- [3.1.3 Documentation](#)
- [3.1.4 Documentation](#)
- [3.1.5 Documentation](#)
- [3.1.6 Documentation](#)
- [3.1.7 Documentation](#)
- [3.1.8 Documentation](#)
- [3.1.9 Documentation](#)
- [3.1.10 Documentation](#)



- [3.1.11 Documentation](#)
- [3.1.12 Documentation](#)
- [3.1.13 Documentation](#)
- [3.1.14 Documentation](#)
- [3.1.15 Documentation](#)
- [3.1.16 Documentation](#)
- [3.1.17 Documentation](#)
- [3.1.18 Documentation](#)
- [3.1.19 Documentation](#)
- [3.1.20 Documentation](#)
- [3.1.21 Documentation](#)
- [3.1.22 Documentation](#)
- [3.1.23 Documentation](#)
- [3.1.24 Documentation](#)
- [3.1.25 Documentation](#)
- [3.1.26 Documentation](#)
- [3.1.27 Documentation](#)
- [3.1.28 Documentation](#)
- [3.1.29 Documentation](#)
- [3.1.30 Documentation](#)
- [3.1.31 Documentation](#)
- [3.1.32 Documentation](#)
- [3.1.33 Documentation](#)

## 19.12 Release Series 3.0 (zeus)

- [3.0 Documentation](#)
- [3.0.1 Documentation](#)
- [3.0.2 Documentation](#)
- [3.0.3 Documentation](#)
- [3.0.4 Documentation](#)

## 19.13 Release Series 2.7 (warrior)

- [2.7 Documentation](#)
- [2.7.1 Documentation](#)
- [2.7.2 Documentation](#)
- [2.7.3 Documentation](#)
- [2.7.4 Documentation](#)

## 19.14 Release Series 2.6 (thud)

- [2.6 Documentation](#)
- [2.6.1 Documentation](#)
- [2.6.2 Documentation](#)
- [2.6.3 Documentation](#)
- [2.6.4 Documentation](#)

## 19.15 Release Series 2.5 (sumo)

- [2.5 Documentation](#)
- [2.5.1 Documentation](#)
- [2.5.2 Documentation](#)
- [2.5.3 Documentation](#)

## 19.16 Release Series 2.4 (rocko)

- [2.4 Documentation](#)
- [2.4.1 Documentation](#)
- [2.4.2 Documentation](#)
- [2.4.3 Documentation](#)
- [2.4.4 Documentation](#)

## 19.17 Release Series 2.3 (pyro)

- [2.3 Documentation](#)
- [2.3.1 Documentation](#)
- [2.3.2 Documentation](#)
- [2.3.3 Documentation](#)

- [2.3.4 Documentation](#)

## 19.18 Release Series 2.2 (morty)

- [2.2 Documentation](#)
- [2.2.1 Documentation](#)
- [2.2.2 Documentation](#)
- [2.2.3 Documentation](#)
- [2.2.4 Documentation](#)

## 19.19 Release Series 2.1 (krogoth)

- [2.1 Documentation](#)
- [2.1.1 Documentation](#)
- [2.1.2 Documentation](#)
- [2.1.3 Documentation](#)

## 19.20 Release Series 2.0 (jethro)

- [1.9 Documentation](#)
- [2.0 Documentation](#)
- [2.0.1 Documentation](#)
- [2.0.2 Documentation](#)
- [2.0.3 Documentation](#)

## 19.21 Release Series 1.8 (fido)

- [1.8 Documentation](#)
- [1.8.1 Documentation](#)
- [1.8.2 Documentation](#)

## 19.22 Release Series 1.7 (dizzy)

- [1.7 Documentation](#)
- [1.7.1 Documentation](#)
- [1.7.2 Documentation](#)
- [1.7.3 Documentation](#)

## 19.23 Release Series 1.6 (daisy)

- [1.6 Documentation](#)
- [1.6.1 Documentation](#)
- [1.6.2 Documentation](#)
- [1.6.3 Documentation](#)

## 19.24 Release Series 1.5 (dora)

- [1.5 Documentation](#)
- [1.5.1 Documentation](#)
- [1.5.2 Documentation](#)
- [1.5.3 Documentation](#)
- [1.5.4 Documentation](#)

## 19.25 Release Series 1.4 (dylan)

- [1.4 Documentation](#)
- [1.4.1 Documentation](#)
- [1.4.2 Documentation](#)
- [1.4.3 Documentation](#)
- [1.4.4 Documentation](#)

## 19.26 Release Series 1.3 (danny)

- [1.3 Documentation](#)
- [1.3.1 Documentation](#)
- [1.3.2 Documentation](#)

## 19.27 Release Series 1.2 (denzil)

- [1.2 Documentation](#)
- [1.2.1 Documentation](#)
- [1.2.2 Documentation](#)

## 19.28 Release Series 1.1 (edison)

- [1.1 Documentation](#)
- [1.1.1 Documentation](#)
- [1.1.2 Documentation](#)

## 19.29 Release Series 1.0 (bernard)

- [1.0 Documentation](#)
- [1.0.1 Documentation](#)
- [1.0.2 Documentation](#)

## 19.30 Release Series 0.9 (laverne)

- [0.9 Documentation](#)
- [0.9.1 Documentation](#)



## CAPITOLO 20

---

Indice

---





---

### Download della Documentazione

---

La documentazione può essere scaricata in diversi formati per essere letta offline o su un altro dispositivo. I formati attualmente supportati sono elencati di seguito:

- [EPub](#)
- [PDF](#)



## A

ABIEXTENSION, [274](#)  
 ALLOW\_EMPTY, [274](#)  
 ALTERNATIVE, [274](#)  
 ALTERNATIVE\_LINK\_NAME, [274](#)  
 ALTERNATIVE\_PRIORITY, [275](#)  
 ALTERNATIVE\_TARGET, [275](#)  
 ANY\_OF\_DISTRO\_FEATURES, [275](#)  
 APPEND, [275](#)  
 AR, [276](#)  
 ARCHIVER\_MODE, [276](#)  
 AS, [276](#)  
 ASSUME\_PROVIDED, [276](#)  
 ASSUME\_SHLIBS, [276](#)  
 AUTO\_LIBNAME\_PKGS, [277](#)  
 AUTO\_SYSLINUXMENU, [277](#)  
 AUTOREV, [277](#)  
 AUTOTOOLS\_SCRIPT\_PATH, [277](#)  
 AVAILTUNES, [277](#)  
 AZ\_SAS, [277](#)

## B

B, [278](#)  
 BAD\_RECOMMENDATIONS, [278](#)  
 BAREBOX\_BINARY, [278](#)  
 BAREBOX\_CONFIG, [278](#)  
 BASE\_LIB, [279](#)  
 BASE\_WORKDIR, [279](#)  
 BB\_ALLOWED\_NETWORKS, [279](#)  
 BB\_BASEHASH\_IGNORE\_VARS, [279](#)  
 BB\_CACHEDIR, [279](#)  
 BB\_CHECK\_SSL\_CERTS, [279](#)  
 BB\_CONF\_FRAGMENT\_DESCRIPTION, [280](#)

BB\_CONF\_FRAGMENT\_SUMMARY, [280](#)  
 BB\_CONSOLELOG, [280](#)  
 BB\_CURRENT\_MC, [280](#)  
 BB\_CURRENTTASK, [280](#)  
 BB\_DEFAULT\_TASK, [280](#)  
 BB\_DEFAULT\_UMASK, [280](#)  
 BB\_DEFER\_BBCLASSES, [280](#)  
 BB\_DISKMON\_DIRS, [280](#)  
 BB\_DISKMON\_WARNINTERVAL, [281](#)  
 BB\_ENV\_PASSTHROUGH, [282](#)  
 BB\_ENV\_PASSTHROUGH\_ADDITIONS, [282](#)  
 BB\_FETCH\_PREMIRRORONLY, [282](#)  
 BB\_FILENAME, [282](#)  
 BB\_GENERATE\_MIRROR\_TARBALLS, [282](#)  
 BB\_GENERATE\_SHALLOW\_TARBALLS, [283](#)  
 BB\_GIT\_DEFAULT\_DESTSUFFIX, [283](#)  
 BB\_GIT\_SHALLOW, [283](#)  
 BB\_GIT\_SHALLOW\_DEPTH, [283](#)  
 BB\_HASHCHECK\_FUNCTION, [283](#)  
 BB\_HASHCONFIG\_IGNORE\_VARS, [283](#)  
 BB\_HASHSERVE, [283](#)  
 BB\_HASHSERVE\_UPSTREAM, [283](#)  
 BB\_INVALIDIDCONF, [283](#)  
 BB\_LOADFACTOR\_MAX, [283](#)  
 BB\_LOGCONFIG, [283](#)  
 BB\_LOGFMT, [283](#)  
 BB\_MULTI\_PROVIDER\_ALLOWED, [283](#)  
 BB\_NICE\_LEVEL, [283](#)  
 BB\_NO\_NETWORK, [284](#)  
 BB\_NUMBER\_PARSE\_THREADS, [284](#)  
 BB\_NUMBER\_THREADS, [284](#)  
 BB\_ORIGENV, [284](#)  
 BB\_PRESERVE\_ENV, [284](#)

BB\_PRESSURE\_MAX\_CPU, [284](#)  
BB\_PRESSURE\_MAX\_IO, [284](#)  
BB\_PRESSURE\_MAX\_MEMORY, [285](#)  
BB\_RUNFMT, [285](#)  
BB\_RUNTASK, [285](#)  
BB\_SCHEDULER, [285](#)  
BB\_SCHEDULERS, [285](#)  
BB\_SERVER\_TIMEOUT, [285](#)  
BB\_SETSCENE\_DEPVALID, [285](#)  
BB\_SIGNATURE\_EXCLUDE\_FLAGS, [285](#)  
BB\_SIGNATURE\_HANDLER, [285](#)  
BB\_SRCREV\_POLICY, [285](#)  
BB\_STRICT\_CHECKSUM, [285](#)  
BB\_TASK\_IONICE\_LEVEL, [285](#)  
BB\_TASK\_NICE\_LEVEL, [285](#)  
BB\_TASKHASH, [285](#)  
BB\_USE\_HOME\_NPMRC, [285](#)  
BB\_VERBOSE\_LOGS, [286](#)  
BB\_WORKERCONTEXT, [286](#)  
BBCLASSEXTEND, [286](#)  
BBDEBUG, [286](#)  
BBFILE\_COLLECTIONS, [286](#)  
BBFILE\_PATTERN, [286](#)  
BBFILE\_PRIORITY, [286](#)  
BBFILES, [287](#)  
BBFILES\_DYNAMIC, [287](#)  
BBINCLUDED, [287](#)  
BBINCLUDELOGS, [287](#)  
BBINCLUDELOGS\_LINES, [287](#)  
BBLAYERS, [288](#)  
BBLAYERS\_FETCH\_DIR, [288](#)  
BBMASK, [288](#)  
BBMULTICONFIG, [289](#)  
BBPATH, [289](#)  
BBSERVER, [289](#)  
BBTARGETS, [289](#)  
BINCONFIG, [289](#)  
BINCONFIG\_GLOB, [289](#)  
BitBake, [136](#)  
BITBAKE\_UI, [290](#)  
Board Support Package (*BSP*), [136](#)  
BP, [290](#)  
BPN, [290](#)  
BUGTRACKER, [290](#)  
BUILD\_AR, [290](#)  
BUILD\_ARCH, [290](#)  
BUILD\_AS, [290](#)  
BUILD\_AS\_ARCH, [291](#)  
BUILD\_CC, [291](#)  
BUILD\_CC\_ARCH, [291](#)  
BUILD\_CCLD, [291](#)  
BUILD\_CFLAGS, [291](#)  
BUILD\_CPP, [291](#)  
BUILD\_CPPFLAGS, [292](#)  
BUILD\_CXX, [292](#)  
BUILD\_CXXFLAGS, [292](#)  
BUILD\_FC, [292](#)  
BUILD\_LD, [292](#)  
BUILD\_LD\_ARCH, [292](#)  
BUILD\_LDFLAGS, [292](#)  
BUILD\_NM, [293](#)  
BUILD\_OBJCOPY, [293](#)  
BUILD\_OBJDUMP, [293](#)  
BUILD\_OPTIMIZATION, [293](#)  
BUILD\_OS, [293](#)  
BUILD\_PREFIX, [293](#)  
BUILD\_RANLIB, [294](#)  
BUILD\_READSELF, [294](#)  
BUILD\_STRIP, [294](#)  
BUILD\_SYS, [294](#)  
BUILD\_VENDOR, [294](#)  
BUILDDIR, [294](#)  
BUILDHISTORY\_COMMIT, [295](#)  
BUILDHISTORY\_COMMIT\_AUTHOR, [295](#)  
BUILDHISTORY\_DIR, [295](#)  
BUILDHISTORY\_FEATURES, [295](#)  
BUILDHISTORY\_IMAGE\_FILES, [296](#)  
BUILDHISTORY\_PATH\_PREFIX\_STRIP, [296](#)  
BUILDHISTORY\_PUSH\_REPO, [296](#)  
BUILDNAME, [296](#)  
BUILDSDK\_CFLAGS, [296](#)  
BUILDSDK\_CPPFLAGS, [296](#)  
BUILDSDK\_CXXFLAGS, [296](#)  
BUILDSDK\_LDFLAGS, [297](#)  
BUILDSTATS\_BASE, [297](#)  
buildtools, [137](#)  
buildtools-extended, [138](#)  
buildtools-make, [138](#)  
Built-in Fragment, [138](#)  
BUSYBOX\_SPLIT\_SUID, [297](#)

## C

CACHE, [297](#)

CARGO\_INSTALL\_LIBRARIES, [297](#)

CARGO\_PROFILE, [297](#)

CC, [297](#)

CCACHE\_DISABLE, [297](#)

CCACHE\_NATIVE\_RECIPES\_ALLOWED, [297](#)

CCACHE\_TOP\_DIR, [297](#)

CCLD, [297](#)

CFLAGS, [297](#)

CHECKLAYER\_REQUIRED\_TESTS, [298](#)

Classi, [138](#)

CLASSOEVERIDE, [298](#)

CLEANBROKEN, [298](#)

COMBINED\_FEATURES, [298](#)

COMMERCIAL\_AUDIO\_PLUGINS, [299](#)

COMMERCIAL\_VIDEO\_PLUGINS, [299](#)

COMMON\_LICENSE\_DIR, [299](#)

COMPATIBLE\_HOST, [299](#)

COMPATIBLE\_MACHINE, [299](#)

COMPLEMENTARY\_GLOB, [300](#)

COMPONENTS\_DIR, [300](#)

CONF\_VERSION, [300](#)

CONFFILES, [300](#)

CONFIG\_INITRAMFS\_SOURCE, [301](#)

CONFIG\_SITE, [301](#)

Configuration Fragment, [139](#)

CONFIGURE\_FLAGS, [301](#)

CONFIGURE\_SCRIPT, [301](#)

CONFLICT\_COMBINED\_FEATURES, [301](#)

CONFLICT\_DISTRO\_FEATURES, [302](#)

CONFLICT\_IMAGE\_FEATURES, [302](#)

CONFLICT\_MACHINE\_FEATURES, [302](#)

CONFLICT\_TUNE\_FEATURES, [302](#)

Container Layer, [140](#)

CONVERSION\_CMD, [302](#)

COPY\_LIC\_DIRS, [302](#)

COPY\_LIC\_MANIFEST, [303](#)

COPYLEFT\_LICENSE\_EXCLUDE, [303](#)

COPYLEFT\_LICENSE\_INCLUDE, [303](#)

COPYLEFT\_PN\_EXCLUDE, [303](#)

COPYLEFT\_PN\_INCLUDE, [303](#)

COPYLEFT\_RECIPE\_TYPES, [304](#)

CORE\_IMAGE\_EXTRA\_INSTALL, [304](#)

COREBASE, [304](#)

COREBASE\_FILES, [304](#)

CPP, [304](#)

CPPFLAGS, [304](#)

CROSS\_COMPILE, [304](#)

Cross-Development Toolchain, [140](#)

CVE\_CHECK\_IGNORE, [305](#)

CVE\_CHECK\_MANIFEST\_JSON, [305](#)

CVE\_CHECK\_SKIP\_RECIPE, [305](#)

CVE\_CHECK\_STATUSMAP, [305](#)

CVE\_CHECK\_VEX\_JUSTIFICATION, [305](#)

CVE\_PRODUCT, [305](#)

CVE\_STATUS, [305](#)

CVE\_STATUS\_GROUPS, [306](#)

CVE\_VERSION, [306](#)

CXX, [306](#)

CXXFLAGS, [306](#)

## D

D, [306](#)

DATE, [306](#)

DATETIME, [307](#)

DEBIAN\_NOAUTONAME, [307](#)

DEBIANNAME, [307](#)

DEBUG\_BUILD, [307](#)

DEBUG\_OPTIMIZATION, [307](#)

DEBUG\_PREFIX\_MAP, [307](#)

DEFAULT\_PREFERENCE, [307](#)

DEFAULT\_TIMEZONE, [307](#)

DEFAULTTUNE, [308](#)

DEPENDS, [308](#)

DEPLOY\_DIR, [309](#)

DEPLOY\_DIR\_DEB, [309](#)

DEPLOY\_DIR\_IMAGE, [309](#)

DEPLOY\_DIR\_IPK, [310](#)

DEPLOY\_DIR\_RPM, [310](#)

DEPLOYDIR, [310](#)

DESCRIPTION, [310](#)

DEV\_PKG\_DEPENDENCY, [310](#)

Directory di Build, [136](#)

DISABLE\_STATIC, [310](#)

DISTRO, [311](#)

DISTRO\_CODENAME, [311](#)

DISTRO\_EXTRA\_RDEPENDS, [311](#)

DISTRO\_EXTRA\_RRECOMMENDS, [311](#)

DISTRO\_FEATURES, [312](#)

DISTRO\_FEATURES\_DEFAULTS, [312](#)  
DISTRO\_FEATURES\_FILTER\_NATIVE, [312](#)  
DISTRO\_FEATURES\_FILTER\_NATIVESDK, [312](#)  
DISTRO\_FEATURES\_NATIVE, [312](#)  
DISTRO\_FEATURES\_NATIVESDK, [312](#)  
DISTRO\_FEATURES\_OPTED\_OUT, [312](#)  
DISTRO\_NAME, [313](#)  
DISTRO\_VERSION, [313](#)  
DISTROOVERRIDES, [313](#)  
DL\_DIR, [313](#)  
DOC\_COMPRESS, [314](#)  
DT\_FILES, [314](#)  
DT\_FILES\_PATH, [314](#)  
DT\_PADDING\_SIZE, [314](#)

## E

EFI\_ARCH, [314](#)  
EFI\_PROVIDER, [314](#)  
EFI\_UKI\_DIR, [315](#)  
EFI\_UKI\_PATH, [315](#)  
ENABLE\_BINARY\_LOCALE\_GENERATION, [315](#)  
ERR\_REPORT\_DIR, [315](#)  
ERROR\_QA, [315](#)  
ESDK\_CLASS\_INHERIT\_DISABLE, [315](#)  
ESDK\_LOCALCONF\_ALLOW, [315](#)  
ESDK\_LOCALCONF\_REMOVE, [316](#)  
EXCLUDE\_FROM\_SHLIBS, [316](#)  
EXCLUDE\_FROM\_WORLD, [316](#)  
EXTENDPE, [317](#)  
EXTENDPKG, [317](#)  
Extensible Software Development Kit (*eSDK*),  
[140](#)  
EXTERNAL\_KERNEL\_DEVICETREE, [317](#)  
EXTERNAL\_KERNEL\_TOOLS, [317](#)  
EXTERNAL\_TOOLCHAIN, [317](#)  
EXTERNALSRC, [317](#)  
EXTERNALSRC\_BUILD, [317](#)  
EXTRA\_AUTORECONF, [318](#)  
EXTRA\_IMAGE\_FEATURES, [318](#)  
EXTRA\_IMAGECMD, [319](#)  
EXTRA\_IMAGEDEPENDS, [319](#)  
EXTRA\_OECMAKE, [319](#)  
EXTRA\_OECONF, [319](#)  
EXTRA\_OEMAKE, [319](#)  
EXTRA\_OEMESON, [319](#)

EXTRA\_OESCONS, [319](#)  
EXTRA\_USERS\_PARAMS, [320](#)  
EXTRANATIVEPATH, [321](#)

## F

FAKEROOT, [321](#)  
FAKEROOTBASEENV, [321](#)  
FAKEROOTCMD, [321](#)  
FAKEROOTDIRS, [321](#)  
FAKEROOTENV, [321](#)  
FAKEROOTNOENV, [321](#)  
FC, [321](#)  
FEATURE\_PACKAGES, [321](#)  
FEED\_DEPLOYDIR\_BASE\_URI, [322](#)  
FETCHCMD, [322](#)  
FILE, [322](#)  
File Append, [136](#)  
File di Configurazione, [139](#)  
FILES, [322](#)  
FILES\_SOLIBSDEV, [323](#)  
FILESEXTRAPATHS, [323](#)  
FILESOVERRIDES, [324](#)  
FILES\_PATH, [324](#)  
FILESYSTEM\_PERMS\_TABLES, [325](#)  
FIRMWARE\_COMPRESSION, [325](#)  
FIT\_ADDRESS\_CELLS, [326](#)  
FIT\_CONF\_DEFAULT\_DTB, [326](#)  
FIT\_CONF\_MAPPINGS, [326](#)  
FIT\_CONF\_PREFIX, [327](#)  
FIT\_DESC, [327](#)  
FIT\_GENERATE\_KEYS, [327](#)  
FIT\_HASH\_ALG, [327](#)  
FIT\_KERNEL\_COMP\_ALG, [327](#)  
FIT\_KERNEL\_SIGN\_ENABLE, [327](#)  
FIT\_KERNEL\_SIGN\_KEYDIR, [327](#)  
FIT\_KERNEL\_SIGN\_KEYNAME, [327](#)  
FIT\_KEY\_GENRSA\_ARGS, [328](#)  
FIT\_KEY\_REQ\_ARGS, [328](#)  
FIT\_KEY\_SIGN\_PKCS, [328](#)  
FIT\_LOADABLE\_ARCH, [328](#)  
FIT\_LOADABLE\_COMPRESSION, [328](#)  
FIT\_LOADABLE\_DESCRIPTION, [328](#)  
FIT\_LOADABLE\_ENTRYPOINT, [329](#)  
FIT\_LOADABLE\_FILENAME, [329](#)  
FIT\_LOADABLE\_LOADADDRESS, [329](#)

FIT\_LOADABLE\_OS, [329](#)  
FIT\_LOADABLE\_TYPE, [329](#)  
FIT\_LOADABLES, [330](#)  
FIT\_MKIMAGE\_EXTRA\_OPTS, [331](#)  
FIT\_OS, [331](#)  
FIT\_PAD\_ALG, [331](#)  
FIT\_SIGN\_ALG, [331](#)  
FIT\_SIGN\_INDIVIDUAL, [332](#)  
FIT\_SIGN\_NUMBITS, [332](#)  
FIT\_UBOOT\_ENV, [332](#)  
FONT\_EXTRA\_RDEPENDS, [332](#)  
FONT\_PACKAGES, [333](#)  
FORCE\_RO\_REMOVE, [333](#)  
FULL\_OPTIMIZATION, [333](#)

## G

GCCPIE, [333](#)  
GCCVERSION, [333](#)  
GDB, [333](#)  
GIR\_EXTRA\_LIBS\_PATH, [333](#)  
GITDIR, [333](#)  
GITHUB\_BASE\_URI, [333](#)  
GLIBC\_GENERATE\_LOCALES, [333](#)  
GO\_IMPORT, [334](#)  
GO\_INSTALL, [334](#)  
GO\_INSTALL\_FILTEROUT, [334](#)  
GO\_WORKDIR, [335](#)  
GROUPADD\_PARAM, [335](#)  
GRUB\_GFXSERIAL, [335](#)  
GRUB\_MKIMAGE\_OPTS, [335](#)  
GRUB\_OPTS, [335](#)  
GRUB\_TIMEOUT, [335](#)  
GRUB\_TITLE, [336](#)  
GTKIMMODULES\_PACKAGES, [336](#)

## H

HGDIR, [336](#)  
HOMEPAGE, [336](#)  
Host di Build, [137](#)  
HOST\_ARCH, [336](#)  
HOST\_AS\_ARCH, [336](#)  
HOST\_CC\_ARCH, [336](#)  
HOST\_LD\_ARCH, [336](#)  
HOST\_OS, [337](#)  
HOST\_PREFIX, [337](#)

HOST\_SYS, [337](#)  
HOST\_VENDOR, [337](#)  
HOSTTOOLS, [337](#)  
HOSTTOOLS\_NONFATAL, [337](#)

## I

IMAGE\_BASENAME, [337](#)  
IMAGE\_BOOT\_FILES, [338](#)  
IMAGE\_BUILDINFO\_FILE, [338](#)  
IMAGE\_BUILDINFO\_VARS, [338](#)  
IMAGE\_CLASSES, [338](#)  
IMAGE\_CMD, [338](#)  
IMAGE\_CONTAINER\_NO\_DUMMY, [339](#)  
IMAGE\_DEVICE\_TABLES, [339](#)  
IMAGE\_EFI\_BOOT\_FILES, [339](#)  
IMAGE\_EXTRA\_PARTITION\_FILES, [339](#)  
IMAGE\_FEATURES, [340](#)  
IMAGE\_FSTYPES, [341](#)  
IMAGE\_FSTYPES\_DEBUGFS, [341](#)  
IMAGE\_GEN\_DEBUGFS, [341](#)  
IMAGE\_INSTALL, [341](#)  
IMAGE\_LINGUAS, [342](#)  
IMAGE\_LINK\_NAME, [342](#)  
IMAGE\_MACHINE\_SUFFIX, [343](#)  
IMAGE\_MANIFEST, [343](#)  
IMAGE\_NAME, [343](#)  
IMAGE\_NAME\_SUFFIX, [343](#)  
IMAGE\_OUTPUT\_MANIFEST, [343](#)  
IMAGE\_OUTPUT\_MANIFEST\_DIR, [344](#)  
IMAGE\_OVERHEAD\_FACTOR, [344](#)  
IMAGE\_PKGTYPE, [344](#)  
IMAGE\_POSTPROCESS\_COMMAND, [344](#)  
IMAGE\_PREPROCESS\_COMMAND, [345](#)  
IMAGE\_ROOTFS, [345](#)  
IMAGE\_ROOTFS\_ALIGNMENT, [345](#)  
IMAGE\_ROOTFS\_EXTRA\_SPACE, [345](#)  
IMAGE\_ROOTFS\_MAXSIZE, [345](#)  
IMAGE\_ROOTFS\_SIZE, [346](#)  
IMAGE\_TYPEDEP, [346](#)  
IMAGE\_TYPES, [346](#)  
IMAGE\_VERSION\_SUFFIX, [348](#)  
IMGDEPLOYDIR, [348](#)  
IMGMANIFESTDIR, [348](#)  
Imagine, [140](#)  
INCOMPATIBLE\_LICENSE, [348](#)

INCOMPATIBLE\_LICENSE\_EXCEPTIONS, [349](#)  
INHERIT, [349](#)  
INHERIT\_DISTRO, [349](#)  
INHIBIT\_AUTOTOOLS\_DEPS, [349](#)  
INHIBIT\_DEFAULT\_DEPS, [350](#)  
INHIBIT\_DEFAULT\_RUST\_DEPS, [350](#)  
INHIBIT\_PACKAGE\_DEBUG\_SPLIT, [350](#)  
INHIBIT\_PACKAGE\_STRIP, [350](#)  
INHIBIT\_SYSROOT\_STRIP, [350](#)  
INHIBIT\_UPDATERCD\_BBCLASS, [351](#)  
INIT\_MANAGER, [351](#)  
Initramfs, [141](#)  
INITRAMFS\_DEPLOY\_DIR\_IMAGE, [351](#)  
INITRAMFS\_FSTYPES, [352](#)  
INITRAMFS\_IMAGE, [352](#)  
INITRAMFS\_IMAGE\_BUNDLE, [352](#)  
INITRAMFS\_IMAGE\_NAME, [353](#)  
INITRAMFS\_LINK\_NAME, [353](#)  
INITRAMFS\_MAXSIZE, [354](#)  
INITRAMFS\_MULTICONFIG, [354](#)  
INITRAMFS\_NAME, [354](#)  
INITRD, [354](#)  
INITRD\_IMAGE, [354](#)  
INITSRIPT\_NAME, [354](#)  
INITSRIPT\_PACKAGES, [354](#)  
INITSRIPT\_PARAMS, [354](#)  
INSANE\_SKIP, [355](#)  
INSTALL\_TIMEZONE\_FILE, [355](#)  
IPK\_FEED\_URI, [355](#)

## K

KARCH, [355](#)  
KBRANCH, [355](#)  
KBUILD\_DEFCONFIG, [356](#)  
KCONF\_AUDIT\_LEVEL, [356](#)  
KCONF\_BSP\_AUDIT\_LEVEL, [357](#)  
KCONFIG\_CONFIG\_ROOTDIR, [357](#)  
KCONFIG\_MODE, [357](#)  
KERNEL\_ALT\_IMAGETYPE, [357](#)  
KERNEL\_ARTIFACT\_NAME, [358](#)  
KERNEL\_CLASSES, [358](#)  
KERNEL\_CONSOLE, [358](#)  
KERNEL\_DANGLING\_FEATURES\_WARN\_ONLY, [358](#)  
KERNEL\_DEBUG\_TIMESTAMPS, [358](#)  
KERNEL\_DEPLOY\_DEPEND, [358](#)

KERNEL\_DEVICETREE, [358](#)  
KERNEL\_DEVICETREE\_BUNDLE, [359](#)  
KERNEL\_DTB\_LINK\_NAME, [359](#)  
KERNEL\_DTB\_NAME, [359](#)  
KERNEL\_DTBDEST, [359](#)  
KERNEL\_DTBVENDOR, [359](#)  
KERNEL\_DTC\_FLAGS, [360](#)  
KERNEL\_EXTRA\_ARGS, [360](#)  
KERNEL\_FEATURES, [360](#)  
KERNEL\_FIT\_LINK\_NAME, [360](#)  
KERNEL\_FIT\_NAME, [360](#)  
KERNEL\_IMAGE\_LINK\_NAME, [361](#)  
KERNEL\_IMAGE\_MAXSIZE, [361](#)  
KERNEL\_IMAGE\_NAME, [361](#)  
KERNEL\_IMAGE\_STRIP\_EXTRA\_SECTIONS, [361](#)  
KERNEL\_IMAGETYPE, [361](#)  
KERNEL\_IMAGETYPES, [361](#)  
KERNEL\_LOCALVERSION, [362](#)  
KERNEL\_MODULE\_AUTOLOAD, [362](#)  
KERNEL\_MODULE\_INSTALL\_PREFIX, [362](#)  
KERNEL\_MODULE\_PROBECONF, [362](#)  
KERNEL\_PACKAGE\_NAME, [362](#)  
KERNEL\_PATH, [362](#)  
KERNEL\_SPLIT\_MODULES, [363](#)  
KERNEL\_SRC, [363](#)  
KERNEL\_STRIP, [363](#)  
KERNEL\_TOOLCHAIN, [363](#)  
KERNEL\_VERSION, [363](#)  
KERNELDEPMODEPEND, [363](#)  
KFEATURE\_DESCRIPTION, [364](#)  
KMACHINE, [364](#)  
KMETA\_AUDIT, [364](#)  
KMETA\_AUDIT\_WERROR, [364](#)  
KMETA\_CONFIG\_FEATURES, [364](#)  
KTYPE, [365](#)

## L

LABELS, [365](#)  
Layer, [141](#)  
LAYERDEPENDS, [365](#)  
LAYERDIR, [365](#)  
LAYERDIR\_RE, [365](#)  
LAYERRECOMMENDS, [365](#)  
LAYERSERIES\_COMPAT, [365](#)  
LAYERVERSION, [365](#)



LD, [366](#)  
 LDFLAGS, [366](#)  
 LEAD\_SONAME, [366](#)  
 LIC\_FILES\_CHKSUM, [366](#)  
 LICENSE, [366](#)  
 LICENSE\_CREATE\_PACKAGE, [367](#)  
 LICENSE\_FLAGS, [367](#)  
 LICENSE\_FLAGS\_ACCEPTED, [367](#)  
 LICENSE\_FLAGS\_DETAILS, [367](#)  
 LICENSE\_PATH, [368](#)  
 LINUX\_KERNEL\_TYPE, [368](#)  
 LINUX\_VERSION, [368](#)  
 LINUX\_VERSION\_EXTENSION, [368](#)  
 LOCALE\_PATHS, [369](#)  
 LOCALE\_UTF8\_IS\_DEFAULT, [369](#)  
 LOG\_DIR, [369](#)  
 LTO, [369](#)  
 LTS, [141](#)

## M

MACHINE, [369](#)  
 MACHINE\_ARCH, [370](#)  
 MACHINE\_ESSENTIAL\_EXTRA\_RDEPENDS, [370](#)  
 MACHINE\_ESSENTIAL\_EXTRA\_RRECOMMENDS, [370](#)  
 MACHINE\_EXTRA\_RDEPENDS, [371](#)  
 MACHINE\_EXTRA\_RRECOMMENDS, [371](#)  
 MACHINE\_FEATURES, [372](#)  
 MACHINE\_FEATURES\_DEFAULTS, [372](#)  
 MACHINE\_FEATURES\_OPTED\_OUT, [372](#)  
 MACHINEOVERRIDES, [372](#)  
 MAINTAINER, [372](#)  
 MESON\_BUILDTYPE, [372](#)  
 MESON\_INSTALL\_TAGS, [373](#)  
 MESON\_TARGET, [373](#)  
 Metadata, [142](#)  
 METADATA\_BRANCH, [373](#)  
 METADATA\_REVISION, [373](#)  
 MIME\_XDG\_PACKAGES, [373](#)  
 MIRRORS, [373](#)  
 Mixin, [142](#)  
 MLPREFIX, [373](#)  
 module\_autoload, [374](#)  
 module\_conf, [374](#)  
 MODULE\_TARBALL\_DEPLOY, [374](#)  
 MODULE\_TARBALL\_LINK\_NAME, [374](#)

MODULE\_TARBALL\_NAME, [375](#)  
 MOUNT\_BASE, [375](#)  
 MOUNT\_GROUP, [375](#)  
 MULTIMACH\_TARGET\_SYS, [375](#)

## N

NATIVESBSTRING, [375](#)  
 NM, [375](#)  
 NO\_GENERIC\_LICENSE, [375](#)  
 NO\_RECOMMENDATIONS, [376](#)  
 NOAUTOPACKAGEDDEBUG, [376](#)  
 NON\_MULTILIB\_RECIPES, [376](#)

## O

OBJCOPY, [377](#)  
 OBJDUMP, [377](#)  
 OE\_BINCONFIG\_EXTRA\_MANGLE, [377](#)  
 OE\_FRAGMENTS, [377](#)  
 OE\_FRAGMENTS\_BUILTIN, [377](#)  
 OE\_FRAGMENTS\_METADATA\_VARS, [377](#)  
 OE\_FRAGMENTS\_PREFIX, [377](#)  
 OE\_INIT\_ENV\_SCRIPT, [377](#)  
 OE\_SHARED\_UMASK, [377](#)  
 OE\_TERMINAL, [377](#)  
 OECMAKE\_GENERATOR, [378](#)  
 OEQA\_REPRODUCIBLE\_TEST\_LEAF\_TARGETS, [378](#)  
 OEQA\_REPRODUCIBLE\_TEST\_PACKAGE, [378](#)  
 OEQA\_REPRODUCIBLE\_TEST\_SSTATE\_TARGETS, [378](#)  
 OEQA\_REPRODUCIBLE\_TEST\_TARGET, [378](#)  
 OEROOT, [378](#)  
 OLDEST\_KERNEL, [378](#)  
 OpenEmbedded Build System, [142](#)  
 OpenEmbedded-Core (*OE-Core*), [142](#)  
 OPENSSSH\_HOST\_KEY\_DIR, [379](#)  
 OPENSSSH\_HOST\_KEY\_DIR\_READONLY\_CONFIG, [379](#)  
 OPKG\_MAKE\_INDEX\_EXTRA\_PARAMS, [379](#)  
 OPKGBUILDCMD, [379](#)  
 OVERLAYFS\_ETC\_DEVICE, [379](#)  
 OVERLAYFS\_ETC\_EXPOSE\_LOWER, [379](#)  
 OVERLAYFS\_ETC\_FSTYPE, [379](#)  
 OVERLAYFS\_ETC\_MOUNT\_OPTIONS, [379](#)  
 OVERLAYFS\_ETC\_MOUNT\_POINT, [379](#)  
 OVERLAYFS\_ETC\_USE\_ORIG\_INIT\_NAME, [379](#)  
 OVERLAYFS\_MOUNT\_POINT, [380](#)  
 OVERLAYFS\_QA\_SKIP, [380](#)

OVERLAYFS\_WRITABLE\_PATHS, [380](#)

OVERRIDES, [380](#)

## P

P, [381](#)

P4DIR, [381](#)

Package, [142](#)

Package Groups, [143](#)

PACKAGE\_ADD\_METADATA, [381](#)

PACKAGE\_ARCH, [381](#)

PACKAGE\_ARCHS, [381](#)

PACKAGE\_BEFORE\_PN, [382](#)

PACKAGE\_CLASSES, [382](#)

PACKAGE\_DEBUG\_SPLIT\_STYLE, [382](#)

PACKAGE\_EXCLUDE, [383](#)

PACKAGE\_EXCLUDE\_COMPLEMENTARY, [383](#)

PACKAGE\_EXTRA\_ARCHS, [383](#)

PACKAGE\_FEED\_ARCHS, [383](#)

PACKAGE\_FEED\_BASE\_PATHS, [384](#)

PACKAGE\_FEED\_URIS, [385](#)

PACKAGE\_INSTALL, [385](#)

PACKAGE\_INSTALL\_ATTEMPTONLY, [385](#)

PACKAGE\_NO\_LOCALE, [385](#)

PACKAGE\_PREPROCESS\_FUNCS, [386](#)

PACKAGE\_WRITE\_DEPS, [386](#)

PACKAGECONFIG, [386](#)

PACKAGECONFIG\_CONFARGS, [388](#)

PACKAGEFUNCS, [389](#)

PACKAGEGROUP\_DISABLE\_COMPLEMENTARY, [389](#)

PACKAGES, [389](#)

PACKAGES\_DYNAMIC, [389](#)

PACKAGESPLITFUNCS, [389](#)

PARALLEL\_MAKE, [389](#)

PARALLEL\_MAKEINST, [390](#)

PATCHRESOLVE, [390](#)

PATCHTOOL, [391](#)

PE, [391](#)

PEP517\_WHEEL\_PATH, [391](#)

PERSISTENT\_DIR, [391](#)

PF, [391](#)

PIXBUF\_PACKAGES, [391](#)

PKG, [391](#)

PKG\_CONFIG\_PATH, [391](#)

PKGD, [392](#)

PKGDATA\_DIR, [392](#)

PKGDEST, [392](#)

PKGDESTWORK, [392](#)

PKGE, [392](#)

PKGR, [392](#)

PKGVS, [392](#)

PN, [393](#)

Poky, [143](#)

POPULATE\_SDK\_POST\_HOST\_COMMAND, [393](#)

POPULATE\_SDK\_POST\_TARGET\_COMMAND, [393](#)

PR, [393](#)

PREFERRED\_PROVIDER, [394](#)

PREFERRED\_PROVIDERS, [394](#)

PREFERRED\_RPROVIDER, [394](#)

PREFERRED\_TOOLCHAIN, [395](#)

PREFERRED\_TOOLCHAIN\_NATIVE, [395](#)

PREFERRED\_TOOLCHAIN\_SDK, [395](#)

PREFERRED\_TOOLCHAIN\_TARGET, [395](#)

PREFERRED\_VERSION, [396](#)

PREMIRRORS, [396](#)

PRIORITY, [397](#)

PRIVATE\_LIBS, [397](#)

PROVIDES, [397](#)

PRSERV\_HOST, [398](#)

PRSERV\_UPSTREAM, [399](#)

PSEUDO\_IGNORE\_PATHS, [399](#)

PSEUDO\_INCLUDE\_PATHS, [399](#)

PTEST\_ENABLED, [399](#)

PTEST\_PYTEST\_DIR, [399](#)

PV, [399](#)

PYPI\_PACKAGE, [399](#)

PYPI\_PACKAGE\_EXT, [399](#)

PYPI\_SRC\_URI, [400](#)

PYTHON\_ABI, [400](#)

## Q

QA\_EMPTY\_DIRS, [400](#)

QA\_EMPTY\_DIRS\_RECOMMENDATION, [400](#)

QB\_CMDLINE\_IP\_SLIRP, [400](#)

QB\_CMDLINE\_IP\_TAP, [400](#)

QB\_DEFAULT\_BIOS, [400](#)

QB\_DEFAULT\_FSTYPE, [401](#)

QB\_DEFAULT\_KERNEL, [401](#)

QB\_DRIVE\_TYPE, [401](#)

QB\_GRAPHICS, [401](#)

QB\_KERNEL\_CMDLINE\_APPEND, [401](#)

QB\_MEM, [401](#)  
QB\_NETWORK\_DEVICE, [402](#)  
QB\_NFSROOTFS\_EXTRA\_OPT, [402](#)  
QB\_OPT\_APPEND, [402](#)  
QB\_RNG, [402](#)  
QB\_ROOTFS\_EXTRA\_OPT, [402](#)  
QB\_SERIAL\_OPT, [402](#)  
QB\_SMP, [402](#)  
QB\_TAP\_NAMESERVER, [403](#)  
QB\_TAP\_OPT, [403](#)

## R

RANLIB, [403](#)  
RCONFLICTS, [403](#)  
RDEPENDS, [403](#)  
READELF, [405](#)  
RECIPE\_MAINTAINER, [405](#)  
RECIPE\_NO\_UPDATE\_REASON, [405](#)  
RECIPE\_SYSROOT, [405](#)  
RECIPE\_SYSROOT\_NATIVE, [406](#)  
RECIPE\_UPGRADE\_EXTRA\_TASKS, [406](#)  
Reference Kit, [144](#)  
REPODIR, [406](#)  
REQUIRED\_COMBINED\_FEATURES, [406](#)  
REQUIRED\_DISTRO\_FEATURES, [406](#)  
REQUIRED\_IMAGE\_FEATURES, [406](#)  
REQUIRED\_MACHINE\_FEATURES, [407](#)  
REQUIRED\_TUNE\_FEATURES, [407](#)  
REQUIRED\_VERSION, [407](#)  
RETAIN\_DIRS\_ALWAYS, [407](#)  
RETAIN\_DIRS\_FAILURE, [407](#)  
RETAIN\_DIRS\_GLOBAL\_ALWAYS, [407](#)  
RETAIN\_DIRS\_GLOBAL\_FAILURE, [407](#)  
RETAIN\_ENABLED, [407](#)  
RETAIN\_IGNORE\_TASKS, [407](#)  
RETAIN\_OUTDIR, [408](#)  
RETAIN\_TARBALL\_SUFFIX, [408](#)  
Ricetta, [143](#)  
RM\_WORK\_EXCLUDE, [408](#)  
RM\_WORK\_EXCLUDE\_ITEMS, [408](#)  
ROOT\_HOME, [408](#)  
ROOTFS, [408](#)  
ROOTFS\_POSTINSTALL\_COMMAND, [408](#)  
ROOTFS\_POSTPROCESS\_COMMAND, [409](#)  
ROOTFS\_POSTUNINSTALL\_COMMAND, [409](#)

ROOTFS\_PREPROCESS\_COMMAND, [409](#)  
RPMBUILD\_EXTRA\_PARAMS, [409](#)  
RPROVIDES, [409](#)  
RRECOMMENDS, [409](#)  
RREPLACES, [410](#)  
RSUGGESTS, [411](#)  
RUST\_CHANNEL, [411](#)

## S

S, [411](#)  
SANITY\_REQUIRED\_UTILITIES, [412](#)  
SANITY\_TESTED\_DISTROS, [412](#)  
SBOM, [144](#)  
SBOM\_CVE\_CHECK\_EXPORT\_VARS, [412](#)  
SBOM\_CVE\_CHECK\_EXTRA\_ARGS, [412](#)  
SBOM\_CVE\_CHECK\_SCAN\_SCOPE, [412](#)  
SBOM\_CVE\_CHECK\_SHOW\_WARNINGS, [413](#)  
SDK\_ARCH, [413](#)  
SDK\_ARCHIVE\_TYPE, [413](#)  
SDK\_AS\_ARCH, [413](#)  
SDK\_BUILDINFO\_FILE, [413](#)  
SDK\_CC\_ARCH, [413](#)  
SDK\_CUSTOM\_TEMPLATECONF, [413](#)  
SDK\_DEPLOY, [413](#)  
SDK\_DIR, [413](#)  
SDK\_EXT\_TYPE, [414](#)  
SDK\_FEATURES, [414](#)  
SDK\_HOST\_MANIFEST, [414](#)  
SDK\_INCLUDE\_PKGDATA, [414](#)  
SDK\_INCLUDE\_TOOLCHAIN, [415](#)  
SDK\_LD\_ARCH, [415](#)  
SDK\_NAME, [415](#)  
SDK\_OS, [415](#)  
SDK\_OUTPUT, [415](#)  
SDK\_PACKAGE\_ARCHS, [415](#)  
SDK\_POSTPROCESS\_COMMAND, [416](#)  
SDK\_PREFIX, [416](#)  
SDK\_RECRDEP\_TASKS, [416](#)  
SDK\_SYS, [416](#)  
SDK\_TARGET\_MANIFEST, [416](#)  
SDK\_TARGETS, [416](#)  
SDK\_TITLE, [417](#)  
SDK\_UPDATE\_URL, [417](#)  
SDK\_VENDOR, [417](#)  
SDK\_VERSION, [417](#)

SDK\_ZIP\_OPTIONS, [417](#)  
SDKEXTPATH, [417](#)  
SDKIMAGE\_FEATURES, [417](#)  
SDKMACHINE, [417](#)  
SDKPATH, [418](#)  
SDKPATHINSTALL, [418](#)  
SDKTARGETSYSROOT, [418](#)  
SECTION, [418](#)  
SELECTED\_OPTIMIZATION, [418](#)  
SERIAL\_CONSOLES, [418](#)  
SETUPTOOLS\_BUILD\_ARGS, [418](#)  
SETUPTOOLS\_SETUP\_PATH, [418](#)  
SIGGEN\_EXCLUDE\_SAFE\_RECIPE\_DEPS, [419](#)  
SIGGEN\_EXCLUDERECIPES\_ABISAFE, [419](#)  
SIGGEN\_LOCKEDSIG, [419](#)  
SIGGEN\_LOCKEDSIGS\_TASKSIG\_CHECK, [420](#)  
SIGGEN\_LOCKEDSIGS\_TYPES, [420](#)  
SITEINFO\_BITS, [420](#)  
SITEINFO\_ENDIANNES, [420](#)  
SKIP\_FILEDEPS, [420](#)  
SKIP\_RECIPE, [421](#)  
SOC\_FAMILY, [421](#)  
SOLIBS, [421](#)  
SOLIBSDEV, [421](#)  
Source Directory, [144](#)  
SOURCE\_DATE\_EPOCH, [421](#)  
SOURCE\_MIRROR\_FETCH, [421](#)  
SOURCE\_MIRROR\_URL, [422](#)  
SPDX, [145](#)  
SPDX License Expression, [145](#)  
SPDX\_AUTHORS, [422](#)  
SPDX\_BUILD\_HOST, [423](#)  
SPDX\_CONCLUDED\_LICENSE, [423](#)  
SPDX\_CUSTOM\_ANNOTATION\_VARS, [423](#)  
SPDX\_FILE\_EXCLUDE\_PATTERNS, [424](#)  
SPDX\_GIT\_PURL\_MAPPINGS, [424](#)  
SPDX\_IMAGE\_SUPPLIER, [424](#)  
SPDX\_INCLUDE\_BITBAKE\_PARENT\_BUILD, [425](#)  
SPDX\_INCLUDE\_COMPILED\_SOURCES, [425](#)  
SPDX\_INCLUDE\_KERNEL\_CONFIG, [426](#)  
SPDX\_INCLUDE\_PACKAGECONFIG, [426](#)  
SPDX\_INCLUDE\_SOURCES, [426](#)  
SPDX\_INCLUDE\_VEX, [427](#)  
SPDX\_INVOKED\_BY, [427](#)  
SPDX\_LICENSES, [428](#)  
SPDX\_MULTILIB\_SSTATE\_ARCHS, [428](#)  
SPDX\_NAMESPACE\_PREFIX, [428](#)  
SPDX\_ON\_BEHALF\_OF, [428](#)  
SPDX\_PACKAGE\_SUPPLIER, [428](#)  
SPDX\_PACKAGE\_URL, [429](#)  
SPDX\_PACKAGE\_URLS, [429](#)  
SPDX\_PACKAGE\_VERSION, [429](#)  
SPDX\_PRETTY, [429](#)  
SPDX\_SDK\_SUPPLIER, [429](#)  
SPDX\_UUID\_NAMESPACE, [429](#)  
SPDXLICENSEMAP, [430](#)  
SPECIAL\_PKGSUFFIX, [430](#)  
SPL\_BINARY, [430](#)  
SPL\_DTB\_BINARY, [430](#)  
SPL\_MKIMAGE\_DTCOPTS, [430](#)  
SPL\_SIGN\_ENABLE, [430](#)  
SPL\_SIGN\_KEYDIR, [430](#)  
SPL\_SIGN\_KEYNAME, [431](#)  
SPLASH, [431](#)  
SPLASH\_IMAGES, [431](#)  
SRC\_URI, [431](#)  
SRC\_URI\_OVERRIDES\_PACKAGE\_ARCH, [432](#)  
SRCDATE, [432](#)  
SRCPV, [432](#)  
SRCREV, [432](#)  
SRCREV\_FORMAT, [433](#)  
SRCTREECOVEREDTASKS, [433](#)  
SSTATE\_DIR, [433](#)  
SSTATE\_EXCLUDEDEPS\_SYSROOT, [433](#)  
SSTATE\_MIRROR\_ALLOW\_NETWORK, [434](#)  
SSTATE\_MIRRORS, [434](#)  
SSTATE\_SCAN\_FILES, [434](#)  
SSTATE\_SIG\_KEY, [434](#)  
SSTATE\_SIG\_PASSPHRASE, [435](#)  
SSTATE\_SKIP\_CREATION, [435](#)  
SSTATE\_VALID\_SIGS, [435](#)  
SSTATE\_VERIFY\_SIG, [435](#)  
STABLE\_VERSION\_PARTS, [436](#)  
STAGING\_BASE\_LIBDIR\_NATIVE, [436](#)  
STAGING\_BASELIBDIR, [436](#)  
STAGING\_BINDIR, [436](#)  
STAGING\_BINDIR\_CROSS, [436](#)  
STAGING\_BINDIR\_NATIVE, [436](#)  
STAGING\_DATADIR, [436](#)  
STAGING\_DATADIR\_NATIVE, [436](#)

STAGING\_DIR, [436](#)  
 STAGING\_DIR\_HOST, [437](#)  
 STAGING\_DIR\_NATIVE, [437](#)  
 STAGING\_DIR\_TARGET, [437](#)  
 STAGING\_ETCDIR\_NATIVE, [438](#)  
 STAGING\_EXECPREFIXDIR, [438](#)  
 STAGING\_INCDIR, [438](#)  
 STAGING\_INCDIR\_NATIVE, [438](#)  
 STAGING\_KERNEL\_BUILDDIR, [438](#)  
 STAGING\_KERNEL\_DIR, [438](#)  
 STAGING\_LIBDIR, [438](#)  
 STAGING\_LIBDIR\_NATIVE, [438](#)  
 STAMP, [438](#)  
 STAMPCLEAN, [438](#)  
 STAMPS\_DIR, [438](#)  
 STRIP, [439](#)  
 SUMMARY, [439](#)  
 SVNDIR, [439](#)  
 SYSINUX\_DEFAULT\_CONSOLE, [439](#)  
 SYSINUX\_OPTS, [439](#)  
 SYSINUX\_SERIAL, [439](#)  
 SYSINUX\_SERIAL\_TTY, [439](#)  
 SYSINUX\_SPLASH, [439](#)  
 Sysroot, [145](#)  
 SYSROOT\_DESTDIR, [440](#)  
 SYSROOT\_DIRS, [440](#)  
 SYSROOT\_DIRS\_IGNORE, [440](#)  
 SYSROOT\_DIRS\_NATIVE, [441](#)  
 SYSROOT\_PREPROCESS\_FUNCS, [442](#)  
 SYSTEMD\_AUTO\_ENABLE, [442](#)  
 SYSTEMD\_BOOT\_CFG, [442](#)  
 SYSTEMD\_BOOT\_ENTRIES, [442](#)  
 SYSTEMD\_BOOT\_TIMEOUT, [442](#)  
 SYSTEMD\_DEFAULT\_TARGET, [442](#)  
 SYSTEMD\_PACKAGES, [443](#)  
 SYSTEMD\_SERVICE, [443](#)  
 SYSVINIT\_ENABLED\_GETTYS, [443](#)

## T

T, [443](#)  
 TARGET\_ARCH, [443](#)  
 TARGET\_AS\_ARCH, [444](#)  
 TARGET\_CC\_ARCH, [444](#)  
 TARGET\_CC\_KERNEL\_ARCH, [444](#)  
 TARGET\_CFLAGS, [444](#)  
 TARGET\_CPPFLAGS, [444](#)  
 TARGET\_CXXFLAGS, [444](#)  
 TARGET\_DBGSRC\_DIR, [445](#)  
 TARGET\_FPU, [445](#)  
 TARGET\_LD\_ARCH, [445](#)  
 TARGET\_LDFLAGS, [445](#)  
 TARGET\_OS, [445](#)  
 TARGET\_PREFIX, [445](#)  
 TARGET\_SYS, [445](#)  
 TARGET\_VENDOR, [446](#)  
 Task, [145](#)  
 TC\_CXX\_RUNTIME, [446](#)  
 TCLIBC, [446](#)  
 TCMODE, [446](#)  
 TEMPLATECONF, [446](#)  
 TEST\_EXPORT\_DIR, [447](#)  
 TEST\_EXPORT\_ONLY, [447](#)  
 TEST\_LOG\_DIR, [447](#)  
 TEST\_POWERCONTROL\_CMD, [447](#)  
 TEST\_POWERCONTROL\_EXTRA\_ARGS, [447](#)  
 TEST\_QEMUBOOT\_TIMEOUT, [447](#)  
 TEST\_SERIALCONTROL\_CMD, [447](#)  
 TEST\_SERIALCONTROL\_CONNECT\_TIMEOUT, [448](#)  
 TEST\_SERIALCONTROL\_EXTRA\_ARGS, [448](#)  
 TEST\_SERIALCONTROL\_PS1, [448](#)  
 TEST\_SERVER\_IP, [448](#)  
 TEST\_SUITES, [448](#)  
 TEST\_TARGET, [449](#)  
 TEST\_TARGET\_IP, [449](#)  
 TESTIMAGE\_AUTO, [449](#)  
 TESTIMAGE\_FAILED\_QA\_ARTIFACTS, [450](#)  
 TESTSDK\_SUITES, [450](#)  
 THISDIR, [450](#)  
 TIME, [450](#)  
 TMPDIR, [450](#)  
 Toaster, [145](#)  
 TOOLCHAIN, [450](#)  
 TOOLCHAIN\_HOST\_TASK, [451](#)  
 TOOLCHAIN\_HOST\_TASK\_ESDK, [451](#)  
 TOOLCHAIN\_NATIVE, [451](#)  
 TOOLCHAIN\_OPTIONS, [451](#)  
 TOOLCHAIN\_OUTPUTNAME, [451](#)  
 TOOLCHAIN\_TARGET\_TASK, [451](#)  
 TOPDIR, [452](#)  
 TRANSLATED\_TARGET\_ARCH, [452](#)

TUNE\_ARCH, [452](#)  
TUNE\_ASARGS, [452](#)  
TUNE\_CCARGS, [453](#)  
TUNE\_FEATURES, [453](#)  
TUNE\_LDARGS, [453](#)  
TUNE\_PKGARCH, [454](#)  
TUNECONFLICTS, [454](#)  
TUNEVALID, [454](#)

## U

UBOOT\_BINARY, [454](#)  
UBOOT\_CONFIG, [454](#)  
UBOOT\_CONFIG\_BINARY, [455](#)  
UBOOT\_CONFIG\_FRAGMENTS, [455](#)  
UBOOT\_CONFIG\_IMAGE\_FSTYPES, [456](#)  
UBOOT\_CONFIG\_MAKE\_OPTS, [456](#)  
UBOOT\_DTB\_LOADADDRESS, [456](#)  
UBOOT\_DTBO\_LOADADDRESS, [456](#)  
UBOOT\_ENTRYPOINT, [456](#)  
UBOOT\_ENV, [457](#)  
UBOOT\_ENV\_SRC\_SUFFIX, [457](#)  
UBOOT\_ENV\_SUFFIX, [457](#)  
UBOOT\_EXTLINUX, [457](#)  
UBOOT\_EXTLINUX\_CONF\_NAME, [457](#)  
UBOOT\_EXTLINUX\_CONSOLE, [457](#)  
UBOOT\_EXTLINUX\_DEFAULT\_LABEL, [457](#)  
UBOOT\_EXTLINUX\_FDT, [458](#)  
UBOOT\_EXTLINUX\_FDTDIR, [458](#)  
UBOOT\_EXTLINUX\_FDTOVERLAYS, [458](#)  
UBOOT\_EXTLINUX\_INITRD, [458](#)  
UBOOT\_EXTLINUX\_INSTALL\_DIR, [459](#)  
UBOOT\_EXTLINUX\_KERNEL\_ARGS, [459](#)  
UBOOT\_EXTLINUX\_KERNEL\_IMAGE, [459](#)  
UBOOT\_EXTLINUX\_LABELS, [459](#)  
UBOOT\_EXTLINUX\_MENU\_DESCRIPTION, [460](#)  
UBOOT\_EXTLINUX\_MENU\_TITLE, [460](#)  
UBOOT\_EXTLINUX\_ROOT, [460](#)  
UBOOT\_EXTLINUX\_TIMEOUT, [460](#)  
UBOOT\_FIT\_ADDRESS\_CELLS, [460](#)  
UBOOT\_FIT\_ARM\_TRUSTED\_FIRMWARE, [461](#)  
UBOOT\_FIT\_ARM\_TRUSTED\_FIRMWARE\_IMAGE, [461](#)  
UBOOT\_FIT\_CONF\_DESC, [461](#)  
UBOOT\_FIT\_CONF\_FIRMWARE, [461](#)  
UBOOT\_FIT\_CONF\_USER\_LOADABLES, [461](#)  
UBOOT\_FIT\_DESC, [461](#)

UBOOT\_FIT\_GENERATE\_KEYS, [462](#)  
UBOOT\_FIT\_HASH\_ALG, [462](#)  
UBOOT\_FIT\_KEY\_GENRSA\_ARGS, [462](#)  
UBOOT\_FIT\_KEY\_REQ\_ARGS, [462](#)  
UBOOT\_FIT\_KEY\_SIGN\_PKCS, [462](#)  
UBOOT\_FIT\_SIGN\_ALG, [462](#)  
UBOOT\_FIT\_SIGN\_NUMBITS, [462](#)  
UBOOT\_FIT\_TEE, [462](#)  
UBOOT\_FIT\_TEE\_IMAGE, [462](#)  
UBOOT\_FIT\_USER\_SETTINGS, [463](#)  
UBOOT\_FITIMAGE\_ENABLE, [464](#)  
UBOOT\_FRAGMENTS, [464](#)  
UBOOT\_INITIAL\_ENV\_BINARY, [465](#)  
UBOOT\_INITIAL\_ENV\_BINARY\_REDUND, [465](#)  
UBOOT\_INITIAL\_ENV\_BINARY\_SIZE, [465](#)  
UBOOT\_LOADADDRESS, [465](#)  
UBOOT\_LOCALVERSION, [466](#)  
UBOOT\_MACHINE, [466](#)  
UBOOT\_MAKE\_OPTS, [466](#)  
UBOOT\_MAKE\_TARGET, [466](#)  
UBOOT\_MKIMAGE, [466](#)  
UBOOT\_MKIMAGE\_DTCOPTS, [466](#)  
UBOOT\_MKIMAGE\_KERNEL\_TYPE, [466](#)  
UBOOT\_MKIMAGE\_SIGN, [466](#)  
UBOOT\_MKIMAGE\_SIGN\_ARGS, [466](#)  
UBOOT\_RD\_ENTRYPOINT, [467](#)  
UBOOT\_RD\_LOADADDRESS, [467](#)  
UBOOT\_SIGN\_ENABLE, [467](#)  
UBOOT\_SIGN\_KEYDIR, [467](#)  
UBOOT\_SIGN\_KEYNAME, [467](#)  
UBOOT\_SUFFIX, [467](#)  
UBOOT\_TARGET, [467](#)  
UBOOT\_VERSION, [467](#)  
UKI\_CMDLINE, [467](#)  
UKI\_CONFIG\_FILE, [468](#)  
UKI\_DEVICETREE, [468](#)  
UKI\_FILENAME, [468](#)  
UKI\_KERNEL\_FILENAME, [468](#)  
UKI\_SB\_CERT, [468](#)  
UKI\_SB\_KEY, [468](#)  
UKIFY\_CMD, [468](#)  
UNINATIVE\_CHECKSUM, [468](#)  
UNINATIVE\_URL, [468](#)  
UNKNOWN\_CONFIGURE\_OPT\_IGNORE, [468](#)  
UNPACKDIR, [469](#)

UPDATERCPN, [469](#)  
Upstream, [145](#)  
UPSTREAM\_CHECK\_COMMITS, [469](#)  
UPSTREAM\_CHECK\_GITTAGREGEX, [469](#)  
UPSTREAM\_CHECK\_REGEX, [469](#)  
UPSTREAM\_CHECK\_URI, [469](#)  
UPSTREAM\_STABLE\_RELEASE\_REGEX, [469](#)  
UPSTREAM\_VERSION\_UNKNOWN, [470](#)  
USE\_DEVFS, [470](#)  
USE\_NLS, [470](#)  
USE\_VT, [470](#)  
USER\_CLASSES, [470](#)  
USERADD\_DEPENDS, [471](#)  
USERADD\_ERROR\_DYNAMIC, [471](#)  
USERADD\_GID\_TABLES, [471](#)  
USERADD\_PACKAGES, [471](#)  
USERADD\_PARAM, [472](#)  
USERADD\_UID\_TABLES, [472](#)  
USERADDEXTENSION, [472](#)  
USERMOD\_PARAM, [473](#)

## V

VIRTUAL-RUNTIME, [473](#)

## W

WARN\_QA, [473](#)  
WATCHDOG\_RUNTIME\_SEC, [473](#)  
WATCHDOG\_TIMEOUT, [473](#)  
WESTON\_USER, [474](#)  
WESTON\_USER\_HOME, [474](#)  
WIC\_CREATE\_EXTRA\_ARGS, [474](#)  
WIC\_SECTOR\_SIZE, [474](#)  
WIRELESS\_DAEMON, [474](#)  
WKS\_FILE, [474](#)  
WKS\_FILE\_DEPENDS, [474](#)  
WKS\_FILES, [475](#)  
WORKDIR, [475](#)

## X

XSERVER, [475](#)  
XZ\_MEMLIMIT, [476](#)  
XZ\_THREADS, [476](#)

## Z

ZSTD\_COMPRESSION\_LEVEL, [476](#)  
ZSTD\_THREADS, [476](#)