## » spotinst\_elastigroup\_aws

Provides a Spotinst AWS group resource.

## » Example Usage

```
# Create an Elastigroup
resource "spotinst_elastigroup_aws" "default-elastigroup" {
            = "default-elastigroup"
 description = "created by Terraform"
 product = "Linux/UNIX"
 max_size
                  = 0
                  = 0
 min_size
 desired_capacity = 0
 capacity_unit = "weight"
            = "us-west-2"
 region
 subnet_ids = ["sb-123456", "sb-456789"]
                      = "ami-a27d8fda"
  image_id
 iam_instance_profile = "iam-profile"
                      = "my-key.ssh"
 key_name
                   = ["sg-123456"]
 security_groups
                     = "echo hello world"
 user_data
 enable_monitoring = false
 ebs_optimized
                      = false
                   = raise
= "default"
 placement_tenancy
 instance_types_ondemand
                              = "m3.2xlarge"
                              = ["m3.xlarge", "m3.2xlarge"]
  instance_types_spot
 instance_types_preferred_spot = ["m3.xlarge"]
 instance_types_weights = [
   instance_type = "c3.large"
   weight
              = 10
 },
   instance_type = "c4.xlarge"
   weight
             = 16
 }]
```

```
= "balanced"
orientation
fallback_to_ondemand = false
cpu_credits
                     = "unlimited"
wait_for_capacity
                         = 5
wait_for_capacity_timeout = 300
scaling_up_policy {
 policy_name
                    = "Default Scaling Up Policy"
 metric_name
                    = "DefaultQueuesDepth"
  statistic
                    = "average"
                    = "none"
 unit
  adjustment
                    = 1
                    = "custom"
 namespace
                    = 100
 threshold
                    = 60
 period
  evaluation\_periods = 5
                    = 300
  cooldown
}
scaling_down_policy {
 policy_name
               = "Default Scaling Down Policy"
 metric_name
                  = "DefaultQueuesDepth"
  statistic
                   = "average"
                    = "none"
 unit
  adjustment
                   = 1
                   = "custom"
 namespace
  threshold
                    = 10
 period
                    = 60
  evaluation_periods = 10
                   = 300
  cooldown
}
tags = [
  key = "Env"
  value = "production"
},
  key = "Name"
   value = "default-production"
},
  key = "Project"
  value = "app_v2"
}
```

```
lifecycle {
   ignore_changes = [
     "desired_capacity",
   ]
}
```

## » Argument Reference

The following arguments are supported:

- name (Required) The group name.
- description (Optional) The group description.
- product (Required) Operation system type. Valid values: "Linux/UNIX", "SUSE Linux", "Windows". For EC2 Classic instances: "Linux/UNIX (Amazon VPC)", "SUSE Linux (Amazon VPC)", "Windows (Amazon VPC)".
- availability\_zones (Optional) List of Strings of availability zones. Note: When this parameter is set, subnet\_ids should be left unused.
- subnet\_ids (Optional) List of Strings of subnet identifiers. Note: When this parameter is set, availability\_zones should be left unused.
- region (Optional) The AWS region your group will be created in. Note:
   This parameter is required if you specify subnets (through subnet\_ids).
   This parameter is optional if you specify Availability Zones (through availability zones).
- preferred\_availability\_zones The AZs to prioritize when launching Spot instances. If no markets are available in the Preferred AZs, Spot instances are launched in the non-preferred AZs. Note: Must be a sublist of availability\_zones and orientation value must not be "equalAzDistribution".
- max\_size (Optional; Required if using scaling policies) The maximum number of instances the group should have at any time.
- min\_size (Optional; Required if using scaling policies) The minimum number of instances the group should have at any time.
- desired\_capacity (Optional) The desired number of instances the group should have at any time.
- capacity\_unit (Optional, Default: "instance") The capacity unit to launch instances by. If not specified, when choosing the weight unit, each

instance will weight as the number of its vCPUs.

- security\_groups (Required) A list of associated security group IDS.
- image\_id (Optional) The ID of the AMI used to launch the instance.
- iam\_instance\_profile (Optional) The ARN or name of an IAM instance profile to associate with launched instances.
- key\_name (Optional) The key name that should be used for the instance.
- enable\_monitoring (Optional) Indicates whether monitoring is enabled for the instance.
- user\_data (Optional) The user data to provide when launching the instance.
- shutdown\_script (Optional) The Base64-encoded shutdown script that executes prior to instance termination, for more information please see: Shutdown Script
- ebs\_optimized (Optional) Enable high bandwidth connectivity between instances and AWS's Elastic Block Store (EBS). For instance types that are EBS-optimized by default this parameter will be ignored.
- placement\_tenancy (Optional) Enable dedicated tenancy. Note: There is a flat hourly fee for each region in which dedicated tenancy is used.
- instance\_types\_ondemand (Required) The type of instance determines your instance's CPU capacity, memory and storage (e.g., m1.small, c1.xlarge).
- instance\_types\_spot (Required) One or more instance types.
- instance\_types\_preferred\_spot (Optional) Prioritize a subset of spot instance types. Must be a subset of the selected spot instance types.
- instance\_types\_weights (Optional) List of weights per instance type for weighted groups. Each object in the list should have the following attributes:
  - weight (Required) Weight per instance type (Integer).
  - instance\_type (Required) Name of instance type (String).
- cpu\_credits (Optional) Controls how T3 instances are launched. Valid values: standard, unlimited.
- fallback\_to\_ondemand (Required) In a case of no Spot instances available, Elastigroup will launch on-demand instances instead.
- wait\_for\_capacity (Optional) Minimum number of instances in a 'HEALTHY' status that is required before continuing. This is ignored when updating with blue/green deployment. Cannot exceed desired\_capacity.

- wait\_for\_capacity\_timeout (Optional) Time (seconds) to wait for instances to report a 'HEALTHY' status. Useful for plans with multiple dependencies that take some time to initialize. Leave undefined or set to 0 to indicate no wait. This is ignored when updating with blue/green deployment.
- orientation (Required, Default: "balanced") Select a prediction strategy. Valid values: "balanced", "costOriented", "equalAzDistribution", "availabilityOriented".
- spot\_percentage (Optional; Required if not using ondemand\_count)
  The percentage of Spot instances that would spin up from the desired\_capacity number.
- ondemand\_count (Optional; Required if not using spot\_percentage) Number of on demand instances to launch in the group. All other instances will be spot instances. When this parameter is set the spot\_percentage parameter is being ignored.
- draining\_timeout (Optional) The time in seconds, the instance is allowed to run while detached from the ELB. This is to allow the instance time to be drained from incoming TCP connections before terminating it, during a scale down operation.
- utilize\_reserved\_instances (Optional) In a case of any available reserved instances, Elastigroup will utilize them first before purchasing Spot instances.
- health\_check\_type (Optional) The service that will perform health checks for the instance. Valid values: "ELB", "HCS", "TARGET\_GROUP", "MLB", "EC2", "MULTAI\_TARGET\_SET", "MLB\_RUNTIME", "K8S\_NODE", "NOMAD\_NODE", "ECS\_CLUSTER\_INSTANCE".
- health\_check\_grace\_period (Optional) The amount of time, in seconds, after the instance has launched to starts and check its health.
- health\_check\_unhealthy\_duration\_before\_replacement (Optional) The amount of time, in seconds, that we will wait before replacing an instance that is running and became unhealthy (this is only applicable for instances that were once healthy).
- tags (Optional) A key/value mapping of tags to assign to the resource.
- elastic\_ips (Optional) A list of AWS Elastic IP allocation IDs to associate to the group instances.
- revert\_to\_spot (Optional) Hold settings for strategy correction replacing On-Demand for Spot instances. Supported Values: "never", "always", "timeWindow"
  - perform\_at (Required) In the event of a fallback to On-Demand instances, select the time period to revert back to Spot. Supported

Arguments – always (default), timeWindow, never. For timeWindow or never to be valid the group must have availabilityOriented OR persistence defined.

- time\_windows - (Optional) Specify a list of time windows for to execute revertToSpot strategy. Time window format: ddd:hh:mm-ddd:hh:mm. Example: Mon:03:00-Wed:02:30

#### » Load Balancers

- elastic\_load\_balancers (Optional) List of Elastic Load Balancers names (ELB).
- target\_group\_arns (Optional) List of Target Group ARNs to register the instances to.
- multai\_target\_sets (Optional) Set of targets to register.
  - target\_set\_id (Required) ID of Multai target set.
  - balancer\_id (Required) ID of Multai Load Balancer.

#### Usage:

```
elastic_load_balancers = ["bal5", "bal2"]
target_group_arns = ["tg-arn"]
multai_target_sets = [{
  target_set_id = "ts-123",
  balancer_id = "bal-123"
},
{
  target_set_id = "ts-234",
  balancer_id = "bal-234"
}]
```

### » Signals

Each signal supports the following:

- name (Required) The name of the signal defined for the group. Valid Values: "INSTANCE\_READY", "INSTANCE\_READY\_TO\_SHUTDOWN"
- timeout (Optional) The signals defined timeout- default is 40 minutes (1800 seconds).

```
signal = {
  name = "INSTANCE_READY_TO_SHUTDOWN"
  timeout = 100
}
```

#### » Scheduled Tasks

Each scheduled\_task supports the following:

- task\_type (Required) The task type to run. Supported task types are: "scale", "backup\_ami", "roll", "scaleUp", "percentageScaleUp", "scaleDown", "percentageScaleDown", "statefulUpdateCapacity".
- cron\_expression (Optional; Required if not using frequency) A valid cron expression. The cron is running in UTC time zone and is in Unix cron format.
- start\_time (Optional; Format: ISO 8601) Set a start time for one time tasks.
- frequency (Optional; Required if not using cron\_expression) The recurrence frequency to run this task. Supported values are "hourly", "daily", "weekly" and "continuous".
- scale\_target\_capacity (Optional) The desired number of instances the group should have.
- scale\_min\_capacity (Optional) The minimum number of instances the group should have.
- scale\_max\_capacity (Optional) The maximum number of instances the group should have.
- is\_enabled (Optional, Default: false) Setting the task to being enabled or disabled. Valid values: true, false.
- target\_capacity (Optional; Only valid for statefulUpdateCapacity) The desired number of instances the group should have.
- min\_capacity (Optional; Only valid for statefulUpdateCapacity) The minimum number of instances the group should have.
- max\_capacity (Optional; Only valid for statefulUpdateCapacity) The maximum number of instances the group should have.
- batch\_size\_percentage (Optional; Required when the task\_type is "roll".) The percentage size of each batch in the scheduled deployment roll
- grace\_period (Optional) The period of time (seconds) to wait before checking a batch's health after it's deployment.
- adjustment (Optional; Min 1) The number of instances to add or remove.
- adjustment\_percentage (Optional; Min 1) The percentage of instances to add or remove.

```
scale_max_capacity = 10
is_enabled = false
target_capacity = 5
min_capacity = 0
max_capacity = 10
batch_size_percentage = 33
grace_period = 300
}
```

## » Scaling Policies

Each scaling\_\*\_policy supports the following:

- namespace (Required) The namespace for the alarm's associated metric.
- metric\_name (Required) The name of the metric, with or without spaces.
- threshold (Required) The value against which the specified statistic is compared.
- policy\_name (Required) The name of the policy.
- statistic (Optional, Default: "average") The metric statistics to return. For information about specific statistics go to Statistics in the Amazon CloudWatch Developer Guide.
- unit (Required) The unit for the alarm's associated metric. Valid values: "percent, "seconds", "microseconds", "milliseconds", "bytes", "kilobytes", "megabytes", "gigabytes", "terabytes", "bits", "kilobits", "megabits", "gigabits", "terabits", "count", "bytes/second", "kilobytes/second", "megabytes/second", "gigabytes/second", "terabytes/second", "kilobits/second", "megabits/second", "gigabits/second", "terabits/second", "count/second", "none".
- is\_enabled (Optional, Default: true) Specifies whether the scaling policy described in this block is enabled.
- period (Optional, Default: 300) The granularity, in seconds, of the returned datapoints. Period must be at least 60 seconds and must be a multiple of 60.
- evaluation\_periods (Optional, Default: 1) The number of periods over which data is compared to the specified threshold.
- cooldown (Optional, Default: 300) The amount of time, in seconds, after a scaling activity completes and before the next scaling activity can start. If this parameter is not specified, the default cooldown period for the group applies.

- dimensions (Optional) A mapping of dimensions describing qualities of the metric.
- operator (Optional, Scale Up Default: gte, Scale Down Default: lte)
  The operator to use in order to determine if the scaling policy is applicable.
  Valid values: "gt", "gte", "lt", "lte".
- source (Optional) The source of the metric. Valid values: "cloudWatch", "spectrum".
- action\_type (Optional; if not using min\_target\_capacity or max\_target\_capacity) The type of action to perform for scaling. Valid values: "adjustment", "percentageAdjustment", "setMaxTarget", "setMinTarget", "updateCapacity".

If you do not specify an action type, you can only use — adjustment, minTargetCapacity, maxTargetCapacity. While using action\_type, please also set the following:

When using adjustment – set the field adjustment When using percentageAdjustment – set the field adjustment When using setMaxTarget – set the field max\_target\_capacity When using setMinTarget – set the field min\_target\_capacity When using updateCapacity – set the fields minimum, maximum, and target

- adjustment (Optional; if not using min\_target\_capacity or max\_target\_capacity;) The number of instances to add/remove to/from the target capacity when scale is needed. Can be used as advanced expression for scaling of instances to add/remove to/from the target capacity when scale is needed. You can see more information here: Advanced expression. Example value: "MAX(currCapacity / 5, value \* 10)"
- min\_target\_capacity (Optional; if not using adjustment; available only for scale up). The number of the desired target (and minimum) capacity
- max\_target\_capacity (Optional; if not using adjustment; available only for scale down). The number of the desired target (and maximum) capacity
- minimum (Optional; if using updateCapacity) The minimal number of instances to have in the group.
- maximum (Optional; if using updateCapacity) The maximal number of instances to have in the group.
- target (Optional; if using updateCapacity) The target number of instances to have in the group.

```
scaling_up_policy = [{
```

```
policy_name = "policy-name"
 metric_name = "CPUUtilization"
 namespace = "AWS/EC2"
         = ""
 source
 statistic = "average"
          = ""
 unit
 cooldown = 60
 is_enabled = false
 dimensions = {
    name = "name-1"
    value = "value-1"
 }
 threshold
                 = 10
 operator = "gt"
 evaluation_periods = 10
                = 60
 period
 // === MIN TARGET =========
 action_type = "setMinTarget"
 min_target_capacity = 1
 // ==============
 // === ADJUSTMENT =========
 # action_type = "adjustment"
 # action_type = "percentageAdjustment"
 # adjustment = "MAX(5,10)"
 // === UPDATE CAPACITY ========
 # action_type = "updateCapacity"
 # minimum = 0
 # maximum = 10
           = 5
 # target
 // ==============
}]
scaling_target_policy = [{
   policy_name = ""
   metric_name = ""
   namespace = ""
   source = ""
   statistic = ""
   unit = ""
```

```
cooldown = 10
target = 1

dimensions = [{
    name = ""
    value = ""
}]
```

### » Network Interfaces

Each of the network\_interface attributes controls a portion of the AWS Instance's "Elastic Network Interfaces". It's a good idea to familiarize yourself with AWS's Elastic Network Interfaces does to understand the implications of using these attributes.

- network\_interface\_id (Optional) The ID of the network interface.
- device\_index (Required) The index of the device on the instance for the network interface attachment.
- description (Required) The description of the network interface.
- private\_ip\_address (Optional) The private IP address of the network interface.
- delete\_on\_termination (Optional) If set to true, the interface is deleted when the instance is terminated.
- secondary\_private\_ip\_address\_count (Optional) The number of secondary private IP addresses.
- associate\_public\_ip\_address (Optional) Indicates whether to assign a public IP address to an instance you launch in a VPC. The public IP address can only be assigned to a network interface for eth0, and can only be assigned to a new network interface, not an existing one.
- associate\_ipv6\_address (Optional) Indicates whether to assign IPV6 addresses to your instance. Requires a subnet with IPV6 CIDR block ranges.

#### » Block Devices

Each of the \*\_block\_device attributes controls a portion of the AWS Instance's "Block Device Mapping". It's a good idea to familiarize yourself with AWS's Block Device Mapping docs to understand the implications of using these attributes.

Each ebs\_block\_device supports the following:

- device\_name (Required) The name of the device to mount.
- snapshot\_id (Optional) The Snapshot ID to mount.
- volume\_type (Optional, Default: "standard") The type of volume. Can be "standard", "gp2", "io1", "st1" or "sc1".
- volume\_size (Optional) The size of the volume in gigabytes.
- iops (Optional) The amount of provisioned IOPS. This must be set with a volume\_type of "io1".
- delete\_on\_termination (Optional) Whether the volume should be destroyed on instance termination.
- encrypted (Optional) Enables EBS encryption on the volume.
- kms\_key\_id (Optional) ID for a user managed CMK under which the EBS Volume is encrypted

Modifying any ebs\_block\_device currently requires resource replacement.

Usage:

```
ebs_block_device = [{
   device name
                         = "/dev/sdb"
                         = ""
   snapshot_id
   volume_type
                         = "gp2"
   volume_size
                         = 8
   iops
   delete_on_termination = true
   encrypted
                         = false
   kms_key_id
                         = "kms-key-01"
 },
 {
   device_name
                          = "/dev/sdc"
                          = ""
   snapshot_id
   volume_type
                         = "gp2"
   volume size
   iops
   delete_on_termination = true
   encrypted
                         = true
   kms_key_id
                         = "kms-key-02"
}]
```

Each ephemeral\_block\_device supports the following:

- device\_name (Required) The name of the block device to mount on the instance.
- virtual\_name (Required) The Instance Store Device Name (e.g. "ephemeral0").

```
ephemeral_block_device = [{
  device_name = "/dev/xvdc"
  virtual_name = "ephemeral0"
}]
```

#### » Stateful

We support instance persistence via the following configurations. all values are boolean. For more information on instance persistence please see: Stateful configuration

- persist\_root\_device (Optional) Boolean, should the instance maintain its root device volumes.
- persist\_block\_devices (Optional) Boolean, should the instance maintain its Data volumes.
- persist\_private\_ip (Optional) Boolean, should the instance maintain its private IP.
- block\_devices\_mode (Optional) String, determine the way we attach the data volumes to the data devices, possible values: "reattach" and "onLaunch" (default is onLaunch).
- private\_ips (Optional) List of Private IPs to associate to the group instances.(e.g. "172.1.1.0"). Please note: This setting will only apply if persistence.persist\_private\_ip is set to true.

#### Usage:

```
persist_root_device = false
persist_block_devices = false
persist_private_ip = true
block_devices_mode = "onLaunch"
private_ips = ["1.1.1.1", "2.2.2.2"]
```

## » Stateful Deallocation

- stateful deallocation (Optional)
  - should\_delete\_images (Optional) For stateful groups: remove persistent images.
  - should\_delete\_network\_interfaces (Optional) For stateful groups: remove network interfaces.

- should\_delete\_volumes (Optional) For stateful groups: remove persistent volumes.
- should\_delete\_snapshots (Optional) For stateful groups: remove snapshots.

#### » Health Check

- health\_check\_type (Optional) The service that will perform
  health checks for the instance. Supported values: "ELB", "HCS",
  "TARGET\_GROUP", "CUSTOM", "K8S\_NODE", "MLB", "EC2", "MULTAI\_TARGET\_SET",
  "MLB\_RUNTIME", "K8S\_NODE", "NOMAD\_NODE", "ECS\_CLUSTER\_INSTANCE".
- health\_check\_grace\_period (Optional) The amount of time, in seconds, after the instance has launched to starts and check its health
- health\_check\_unhealthy\_duration\_before\_replacement (Optional)

  The amount of time, in seconds, that we will wait before replacing an instance that is running and became unhealthy (this is only applicable for instances that were once healthy)

#### Usage:

## » Third-Party Integrations

- integration\_rancher (Optional) Describes the Rancher integration.
  - master\_host (Required) The URL of the Rancher Master host.
  - access\_key (Required) The access key of the Rancher API.
  - secret\_key (Required) The secret key of the Rancher API.
  - version (Optional) The Rancher version. Must be "1" or "2". If this field is omitted, it's assumed that the Rancher cluster is version
    Note that Kubernetes is required when using Rancher version 2. Usage:

```
integration_rancher = {
  master_host = "master_host"
```

```
access_key = "access_key"
secret_key = "secret_key"
version = "2"
}
```

- integration\_ecs (Optional) Describes the EC2 Container Service integration.
  - cluster\_name (Required) The name of the EC2 Container Service cluster
  - autoscale\_is\_enabled (Optional, Default: false) Specifies whether the auto scaling feature is enabled.
  - autoscale\_cooldown (Optional, Default: 300) The amount of time, in seconds, after a scaling activity completes before any further trigger-related scaling activities can start.
  - autoscale\_is\_auto\_config (Optional, Default: false) Enabling the automatic auto-scaler functionality. For more information please see: ECS auto scaler.
  - autoscale\_headroom (Optional) Headroom for the cluster.
    - $\ast$  cpu\_per\_unit (Optional, Default: 0) Cpu units for compute.
    - \* memory\_per\_unit (Optional, Default: 0) RAM units for compute.
    - \* num\_of\_units (Optional, Default: 0) Amount of units for compute.
  - autoscale\_down (Optional) Enabling scale down.
    - \* evaluation\_periods (Optional, Default: 5) Amount of cooldown evaluation periods for scale down.
  - autoscale\_attributes (Optional) A key/value mapping of tags to assign to the resource.

```
key = "test.ecs.key"
value = "test.ecs.value"
}]
}
```

- integration\_codedeploy (Optional) Describes the Code Deploy integration.
  - cleanup\_on\_failure (Optional) Cleanup automatically after a failed deploy.
  - terminate\_instance\_on\_failure (Optional) Terminate the instance automatically after a failed deploy.
  - deployment\_groups (Optional) Specify the deployment groups details.
    - \* application name (Optional) The application name.
    - \* deployment\_group\_name (Optional) The deployment group name.

- integration\_route53 (Optional) Describes the Route53 integration.
  - domains (Required) Collection of one or more domains to register.
    - \* hosted\_zone\_id (Required) The id associated with a hosted zone
    - \* spotinst\_acct\_id (Optional) The Spotinst account ID that is linked to the AWS account that holds the Route 53 hosted Zone ID. The default is the user Spotinst account provided as a URL parameter.
    - \* record\_sets (Required) Collection of records containing authoritative DNS information for the specified domain name.
      - · name (Required) The record set name.
      - · use\_public\_ip (Optional, Default: false) Designates if the IP address should be exposed to connections outside the VPC.

```
integration_route53 = {
  domains = {
```

```
hosted_zone_id = "zone-id"
spotinst_acct_id = "act-123456"

record_sets = {
    name = "foo.example.com"
    use_public_ip = true
    }
}
```

- integration\_docker\_swarm (Optional) Describes the Docker Swarm integration.
  - master\_host (Required) IP or FQDN of one of your swarm managers.
  - master\_port (Required) Network port used by your swarm.
  - autoscale\_is\_enabled (Optional, Default: false) Specifies whether the auto scaling feature is enabled.
  - autoscale\_cooldown (Optional, Default: 300) The amount of time, in seconds, after a scaling activity completes before any further trigger-related scaling activities can start. Minimum 180, must be a multiple of 60.
  - autoscale\_headroom (Optional) An option to set compute reserve for the cluster.
    - \* cpu\_per\_unit (Optional, Default: 0) How much CPU to allocate for headroom unit.
    - \* memory\_per\_unit (Optional, Default: 0) The amount of memory in each headroom unit. Measured in MiB.
    - \* num\_of\_units (Optional, Default: 0) How many units to allocate for headroom unit.
  - autoscale\_down (Optional) Setting for scale down actions.
    - \* evaluation\_periods (Optional, Default: 5) Number of periods over which data is compared. Minimum 3, Measured in consecutive minutes.

```
autoscale_down = {
     evaluation_periods = 3
}
```

- integration\_kubernetes (Optional) Describes the Kubernetes integration.
  - integration\_mode (Required) Valid values: "saas", "pod".
  - cluster\_identifier (Required; if using integration\_mode as pod)
  - api\_server (Required; if using integration\_mode as saas)
  - token (Required; if using integration\_mode as saas) Kubernetes
     Token
  - autoscale\_is\_enabled (Optional, Default: false) Specifies whether the auto scaling feature is enabled.
  - autoscale\_is\_auto\_config (Optional, Default: false) Enabling the automatic k8s auto-scaler functionality. For more information please see: Kubernetes auto scaler.
  - autoscale\_cooldown (Optional, Default: 300) The amount of time, in seconds, after a scaling activity completes before any further trigger-related scaling activities can start.
  - autoscale\_headroom (Optional) An option to set compute reserve for the cluster.
    - \* cpu\_per\_unit (Optional, Default: 0) How much CPU to allocate for headroom unit.
    - \* memory\_per\_unit (Optional, Default: 0) How much Memory allocate for headroom unit.
    - \* num\_of\_units (Optional, Default: 0) How many units to allocate for headroom unit.
  - autoscale\_down (Optional) Setting for scale down actions.
    - \* evaluation\_periods (Optional, Default: 5) How many evaluation periods should accumulate before a scale down action takes place.
  - autoscale\_labels (Optional) A key/value mapping of tags to assign to the resource.

```
autoscale_is_enabled
                           = false
  autoscale_is_auto_config = false
  autoscale_cooldown
                            = 300
  autoscale_headroom = {
    cpu_per_unit
                    = 1024
    memory_per_unit = 512
    num of units
  }
  autoscale_down = {
    evaluation_periods = 300
  }
  autoscale_labels = [{
    key = "test.k8s.key"
    value = "test.k8s.value"
  }]
}
```

- integration\_nomad (Optional) Describes the Nomad integration.
  - master\_host (Required) The URL for the Nomad master host.
  - master\_port (Required) The network port for the master host.
  - acl\_token (Required) Nomad ACL Token
  - autoscale\_is\_enabled (Optional, Default: false) Specifies whether the auto scaling feature is enabled.
  - autoscale\_cooldown (Optional, Default: 300) The amount of time, in seconds, after a scaling activity completes before any further trigger-related scaling activities can start.
  - autoscale\_headroom (Optional) An option to set compute reserve for the cluster.
    - \* cpu\_per\_unit (Optional, Default: 0) How much CPU (MHz) to allocate for headroom unit.
    - \* memory\_per\_unit (Optional, Default: 0) How much Memory allocate for headroom unit.
    - \* num\_of\_units (Optional, Default: 0) How many units of headroom to allocate.
  - autoscale\_down (Optional) Settings for scale down actions.
    - \* evaluation\_periods (Optional, Default: 5) How many evaluation periods should accumulate before a scale down action takes place.
  - autoscale\_constraints (Optional) A key/value mapping of tags to assign to the resource.

```
integration_nomad = {
                           = "my-nomad-host"
    master_host
                           = 9000
    master_port
                           = "top-secret"
    acl_token
    autoscale_is_enabled = false
    autoscale_cooldown
                           = 300
    autoscale_headroom = {
      cpu_per_unit
                      = 1024
      memory_per_unit = 512
      num_of_units
                       = 2
    }
    autoscale down = {
      evaluation_periods = 300
    autoscale_constraints = [{
      key = "test.nomad.key"
      value = "test.nomad.value"
    }]
  }
   • integration_mesosphere - (Optional) Describes the Mesosphere integra-
       - api_server - (Optional) The public IP of the DC/OS Master.
Usage:
  integration_mesosphere = {
    api_server = ""
  }
   • integration_multai_runtime - (Optional) Describes the Multai Run-
     time integration.
       - deployment_id - (Optional) The deployment id you want to get
Usage:
  integration_multai_runtime = {
    deployment_id = ""
  }
   • integration_gitlab - (Optional) Describes the Gitlab integration.
       - runner - (Optional) Settings for Gitlab runner.
           * is_enabled - (Optional, Default: false) Specifies whether the
             integration is enabled.
```

```
Usage:
```

```
integration_gitlab = {
  runner = {
    is_enabled = true
  }
}
• integration_beanstal
  tion.
```

- integration\_beanstalk (Optional) Describes the Beanstalk integration.
  - deployment\_preferences (Optional) Preferences when performing a roll
    - \* automatic\_roll (Required) Should roll perform automatically
    - \* batch\_size\_percentage (Required) Percent size of each batch
    - \* grace\_period (Required) Amount of time to wait between batches
    - \* strategy (Optional) Strategy parameters
      - · action (Required) Action to take
      - $\cdot$   ${\tt should\_drain\_instances}$  (Required) Bool value if to wait to drain instance
  - managed\_actions (Optional) Managed Actions parameters
    - \* platform\_update (Optional) Platform Update parameters
      - · perform\_at (Required) Actions to perform (options: timeWindow, never)
      - time\_window (Required) Time Window for when action occurs ex. Mon:23:50-Tue:00:20
      - · update\_level (Required) Level to update

```
integration_beanstalk = {
                         = "e-3tkmbj7hzc"
  environment_id
 deployment_preferences = {
   automatic_roll
   batch_size_percentage = 100
                          = 90
   grace_period
                          = {
   strategy
                            = "REPLACE_SERVER"
      action
      should_drain_instance = true
   }
 }
 managed_actions
   platform_update = {
                  = "timeWindow"
     perform at
      field_name
                   = "Mon:23:50-Tue:00:20"
```

```
update_level = "minorAndPatch"
}
}
```

## » Update Policy

- update\_policy (Optional)
  - should\_resume\_stateful (Required) This will apply resuming action for Stateful instances in the Elastigroup upon scale up or capacity changes. Example usage will be for Elastigroups that will have scheduling rules to set a target capacity of 0 instances in the night and automatically restore the same state of the instances in the morning.
  - auto\_apply\_tags (Optional) Enables updates to tags without rolling the group when set to true.
  - should\_roll (Required) Sets the enablement of the roll option.
  - wait\_for\_pct\_complete (Optional) For use with should\_roll.
     Sets minimum % of roll required to complete before continuing the plan.
  - wait\_for\_pct\_timeout (Optional) For use with should\_roll.
     Sets how long to wait for the deployed % of a roll to exceed wait\_for\_pct\_complete before continuing the plan.
  - roll\_config (Required) While used, you can control whether the group should perform a deployment after an update to the configuration.
    - \* batch\_size\_percentage (Required) Sets the percentage of the instances to deploy in each batch.
    - \* health\_check\_type (Optional) Sets the health check type to use. Valid values: "EC2", "ECS\_CLUSTER\_INSTANCE", "ELB", "HCS", "MLB", "TARGET\_GROUP", "MULTAI\_TARGET\_SET", "NONE".
    - \* grace\_period (Optional) Sets the grace period for new instances to become healthy.
    - \* wait\_for\_roll\_percentage (Optional) For use with should\_roll. Sets minimum % of roll required to complete before continuing the plan. Required if wait\_for\_roll\_timeout is set.
    - \* wait\_for\_roll\_timeout (Optional) For use with should\_roll.

      Sets how long to wait for the deployed % of a roll to exceed wait\_for\_roll\_percentage before continuing the plan.

      Required if wait\_for\_roll\_percentage is set.

```
update_policy = {
  should_resume_stateful = false
  should roll = false
```

```
auto_apply_tags = false
wait_for_pct_complete = 10
wait_for_pct_timeout = 1500

roll_config = {
  batch_size_percentage = 33
  health_check_type = "ELB"
  grace_period = 300
  wait_for_roll_percentage = 10
  wait_for_roll_timeout = 1500
}
```

#### » Attributes Reference

The following attributes are exported:

• id - The group ID.

# » spotinst\_elastigroup\_aws\_beanstalk

Provides a Spotinst AWS group resource using Elastic Beanstalk.

## » Example Usage

```
resource "spotinst_elastigroup_aws_beanstalk" "elastigoup-aws=beanstalk" {
   name = "example-elastigroup-beanstalk"
   region = "us-west-2"
   product = "Linux/UNIX"

min_size = 0
   max_size = 1
   desired_capacity = 0

beanstalk_environment_name = "example-env"
   beanstalk_environment_id = "e-example"
   instance_types_spot = ["t2.micro", "t2.medium", "t2.large"]
}

deployment_preferences = {
   automatic_roll = true
   batch_size_percentage = 100
```

```
= 90
    grace_period
    strategy = {
        action
                                = "REPLACE SERVER"
        should_drain_instances = true
    }
}
managed_actions = {
    platform update = {
        perform_at
                     = "timeWindow"
        time window = "Mon:23:50-Tue:00:20"
        update_level = "minorAndPatch"
    }
}
```

## » Argument Reference

The following arguments are supported:

- name (Required) The group name.
- region (Required) The AWS region your group will be created in. Cannot be changed after the group has been created.
- description (Optional) The group description.
- product (Required) Operation system type. Valid values: "Linux/UNIX", "SUSE Linux", "Windows". For EC2 Classic instances: "Linux/UNIX (Amazon VPC)", "SUSE Linux (Amazon VPC)", "Windows (Amazon VPC)".
- max\_size (Required) The maximum number of instances the group should have at any time.
- min\_size (Required) The minimum number of instances the group should have at any time.
- desired\_capacity (Required) The desired number of instances the group should have at any time.
- beanstalk\_environment\_name (Optional) The name of an existing Beanstalk environment.
- beanstalk\_environment\_id (Optional) The id of an existing Beanstalk environment.
- instance\_types\_spot (Required) One or more instance types. To maximize the availability of Spot instances, select as many instance types as possible.

- deployment\_preferences (Optional) Preferences when performing a roll
  - automatic\_roll (Required) Should roll perform automatically
  - batch\_size\_percentage (Required) Percent size of each batch
  - grace\_period (Required) Amount of time to wait between batches
  - strategy (Optional) Strategy parameters
    - \* action (Required) Action to take
    - \* should\_drain\_instances (Required) Bool value if to wait to drain instance
- managed\_actions (Optional) Managed Actions parameters
  - platform\_update (Optional) Platform Update parameters
    - \* perform\_at (Required) Actions to perform (options: timeWindow, never)
    - \* time\_window (Required) Time Window for when action occurs ex. Mon:23:50-Tue:00:20
    - \* update\_level (Required) Level to update

## » spotinst\_elastigroup\_azure

Provides a Spotinst elastigroup Azure resource.

## » Example Usage

```
resource "elastigroup_azure" "test_azure_group" {
               = "example_elastigroup_azure"
 resource_group_name = "spotinst-azure"
              = "eastus"
 region
               = "Linux"
 product
 user data = ""
 // --- CAPACITY -----
 min_size = 0
 max_size
         = 1
 desired_capacity = 1
 // -----
 // --- INSTANCE TYPES ------
              = ["standard_a1_v1", "standard_a1_v2"]
 low_priority_sizes = ["standard_a1_v1", "standard_a1_v2"]
```

```
// --- IMAGE ------
image = {
 marketplace = {
  publisher = "Canonical"
  offer = "UbuntuServer"
        = "16.04-LTS"
 }
}
// --- STRATEGY ------
strategy = {
 od_count
 draining_timeout = 300
// --- LOAD BALANCERS -----
load_balancers = [{
          = "MULTAI_TARGET_SET"
 balancer_id = "lb-1ee2e3q"
 target_set_id = "ts-3eq"
 auto_weight = true
}]
// --- HEALTH-CHECKS ------
health_check = {
 health_check_type = "INSTANCE_STATE"
 grace_period = 120
           = true
 auto_healing
// -----
// --- NETWORK -----
network = {
 virtual_network_name = "vname"
 subnet_name = "my-subnet-name"
 resource_group_name = "subnetResourceGroup"
            = true
 assign_public_ip
// --- LOGIN ------
login = {
        = "admin"
 user_name
```

```
ssh_public_key = "33a2s1f3g5a1df5g1ad3f2g1adfg56dfg=="
// -----
// --- SCHEDULED TASK -----
scheduled_task = [{
 is_enabled = true
 cron_expression = "* * * * *"
 task_type = "scale"
 scale_min_capacity = 5
 scale_max_capacity = 8
 adjustment
 adjustment_percentage = 50
 scale target capacity = 6
 batch_size_percentage = 33
                  = 300
 grace_period
}]
```

## » Argument Reference

The following arguments are supported:

- name (Required) The group name.
- region (Required) The region your Azure group will be created in.
- resource\_group\_name (Required) Name of the Resource Group for Elastigroup.
- product (Required) Operation system type. Valid values: "Linux", "Windows".
- max\_size (Required) The maximum number of instances the group should have at any time.
- min\_size (Required) The minimum number of instances the group should have at any time.
- desired\_capacity (Required) The desired number of instances the group should have at any time.
- od\_sizes (Required) Available On-Demand sizes
- low\_priority\_sizes (Required) Available Low-Priority sizes.
- strategy (Required) Describes the deployment strategy.

- low\_priority\_percentage (Optional, Default 100) Percentage of Low Priority instances to maintain. Required if od\_count is not specified.
- od\_count (Optional) Number of On-Demand instances to maintain. Required if low priority percentage is not specified.
- draining\_timeout (Optional, Default 120) Time (seconds) to allow the instance to be drained from incoming TCP connections and detached from MLB before terminating it during a scale-down operation.

#### » Load Balancers

- load\_balancers (Required) Describes a set of one or more classic load balancer target groups and/or Multai load balancer target sets.
- type (Required) The resource type. Valid values: CLASSIC, TAR-GET GROUP, MULTAI TARGET SET.
- balancer\_id (Required) The balancer ID.
- target\_set\_id (Required) The scale set ID associated with the load balancer.
- auto\_weight (Optional, Default: false)

#### » Image

- image (Required) Image of a VM. An image is a template for creating new VMs. Choose from Azure image catalogue (marketplace) or use a custom image.
- publisher (Optional) Image publisher. Required if resource\_group\_name is not specified.
- offer (Optional) Name of the image to use. Required if publisher is specified.
- user\_data (Optional) Base64-encoded MIME user data to make available to the instances.
- sku (Optional) Image's Stock Keeping Unit, which is the specific version of the image. Required if publisher is specified.
- resource\_group\_name (Optional) Name of Resource Group for custom image. Required if publisher not specified.
- image\_name (Optional) Name of the custom image. Required if resource\_group\_name is specified.

```
// market image
image = {
  marketplace = {
    publisher = "Canonical"
            = "UbuntuServer"
    sku
             = "16.04-LTS"
  }
}
// custom image
image = {
  custom = {
    image_name
                        = "customImage"
    resource group name = "resourceGroup"
  }
}
```

#### » Health Check

- health\_check (Optional) Describes the health check configuration.
- health\_check\_type (Optional) Health check used to validate VM health. Valid values: "INSTANCE STATE".
- grace\_period (Optional) Period of time (seconds) to wait for VM to reach healthiness before monitoring for unhealthiness.
- auto\_healing (Optional) Enable auto-healing of unhealthy VMs.

```
health_check = {
  health_check_type = "INSTANCE_STATE"
  grace_period = 120
  auto_healing = true
}
```

## » Network

- network (Required) Defines the Virtual Network and Subnet for your Elastigroup.
- virtual\_network\_name (Required) Name of Vnet.
- subnet\_name (Required) ID of subnet.
- resource\_group\_name (Required) Vnet Resource Group Name.
- assign\_public\_up (Optional, Default: false) Assign a public IP to each VM in the Elastigroup.

```
network = {
  virtual_network_name = "vname"
  subnet name = "my-subnet-name"
```

```
resource_group_name = "subnetResourceGroup"
assign_public_ip = true
}
```

## » Login

- login (Required) Describes the login configuration.
- user\_name (Required) Set admin access for accessing your VMs.
- ssh\_public\_key (Optional) SSH for admin access to Linux VMs. Required for Linux product types.
- password (Optional) Password for admin access to Windows VMs. Required for Windows product types.

## » Scheduling

- scheduled\_task (Optional) Describes the configuration of one or more scheduled tasks.
- is\_enabled (Optional, Default: true) Describes whether the task is enabled. When true the task should run when false it should not run.
- cron\_expression (Required) A valid cron expression (\* \* \* \* \*). The cron is running in UTC time zone and is in Unix cron format Cron Expression Validator Script.
- task\_type (Required) The task type to run. Valid Values: backup\_ami, scale, scaleUp, roll, statefulUpdateCapacity, statefulRecycle.
- scale\_min\_capacity (Optional) The min capacity of the group. Should be used when choosing 'task\_type' of 'scale'.
- scale\_max\_capacity (Optional) The max capacity of the group. Required when 'task\_type' is 'scale'.
- scale\_target\_capacity (Optional) The target capacity of the group. Should be used when choosing 'task\_type' of 'scale'.
- adjustment (Optional) The number of instances to add/remove to/from the target capacity when scale is needed.
- adjustment\_percentage (Optional) The percent of instances to add/remove to/from the target capacity when scale is needed.
- batch\_size\_percentage (Optional) The percentage size of each batch in the scheduled deployment roll. Required when the 'task\_type' is 'roll'.
- grace\_period (Optional) The time to allow instances to become healthy.

```
scheduled_task = [{
  is enabled = true
```

```
cron_expression = "* * * * * *"
task_type = "scale"

scale_min_capacity = 5
scale_max_capacity = 8
adjustment = 2

adjustment_percentage = 50
scale_target_capacity = 6
batch_size_percentage = 33
grace_period = 300
}
```

## » Update Policy

- update\_policy (Optional)
  - should\_roll (Required) Sets the enablement of the roll option.
  - roll\_config (Required) While used, you can control whether the group should perform a deployment after an update to the configuration.
    - \* batch\_size\_percentage (Required) Sets the percentage of the instances to deploy in each batch.
    - \* health\_check\_type (Optional) Sets the health check type to use. Valid values: "INSTANCE\_STATE", "NONE".
    - \* grace\_period (Optional) Sets the grace period for new instances to become healthy.

```
update_policy = {
  should_roll = false

roll_config = {
   batch_size_percentage = 33
   health_check_type = "INSTANCE_STATE"
   grace_period = 300
  }
}
```

# 

Provides a Spotinst elastigroup GCP resource.

## » Example Usage

```
resource "spotinst_elastigroup_gcp" "example" {
                 = "example-gcp"
 description
                 = "spotinst gcp group"
 service_account = "example@myProject.iam.gservicecct.com"
 startup_script = ""
 min_size
                  = 0
 max size
                  = 1
 desired\_capacity = 1
 availability_zones = ["asia-east1-c", "us-central1-a"]
 preemptible_percentage = 50
 # on_demand_count
 fallback_to_od
                        = true
 draining_timeout
                       = 180
                  = [key = "env", value = "staging"]
 labels
                  = ["http", "https"]
 tags
 backend_services_config = {[
     service_name = "spotinst-elb-backend-service"
     ports = {
       port_name = "port-name"
       ports = [8000, 6000]
   },
 ]}
 disks = [
   {
     device_nime = "device"
     mode = "READ_WRITE"
               = "PERSISTENT"
     type
     auto delete = true
     boot = true
     interface = "SCSI"
     initialize_parms = {
       disk_size_gb = 10
       disk_type = "pd-standard"
       source_image = ""
     }
```

```
}
network_interfaces = [
   network = "spot-network"
]
instance_types_on_demand = ["n1-standard-1"]
instance_types_preemptible = ["n1-standard-1", "n1-standard-2"]
instance_types_custom = [
   vCPU
          = 2
   memoryGiB = 7.5
]
subnets = [
  {
             = "asia-east1"
   region
    subnet_names = ""
]
scaling = {
 up = {
   policy_name = "scale_up_1"
             = "stackdriver"
   source
   metric_name = "instance/disk/read_ops_count"
   namespace = "compute"
    statistic = "average"
               = "percent"
    unit
    threshold = 10000
               = 300
    period
               = 300
    cooldown
    operator
               = "gte"
    evaluation_periods = 1
    action = {
     type
                = "adjustment"
      adjustment = 1
    }
```

## » Argument Reference

The following arguments are supported:

- name (Required) The group name.
- description (Optional) The region your GCP group will be created in.
- startup\_script (Optional) Create and run your own startup scripts on your virtual machines to perform automated tasks every time your instance boots up.
- service\_account (Optional) The email of the service account in which the group instances will be launched.
- max\_size (Required) The maximum number of instances the group should have at any time.
- min\_size (Required) The minimum number of instances the group should have at any time.
- desired\_capacity (Required) The desired number of instances the group should have at any time.
- availability\_zones (Required) List of availability zones for the group.
- subnets (Optional) A list of regions and subnets.
- region (Required) The region for the group of subnets.
- subnet\_names (Required) The names of the subnets in the region.
- instance\_types\_preemptible (Required) The preemptible VMs instance type. To maximize cost savings and market availability, select as many types as possible. Required if instance\_types\_on\_demand is not set.
- instance\_types\_on\_demand (Required) The regular VM instance type to use for mixed-type groups and when falling back to on-demand. Required if instance\_types\_preemptible is not set.

- instance\_types\_custom (Required) Defines a set of custom instance types. Required if instance\_types\_preemptible and instance\_types\_on\_demand are not set.
- vCPU (Optional) The number of vCPUs in the custom instance type. GCP has a number of limitations on accepted vCPU values. For more information, see the GCP documentation (here.)[https://cloud.google.com/compute/docs/instances/creating-instance-with-custom-machine-type#specifications]
- memory\_gib (Optional) The memory (in GiB) in the custom instance types. GCP has a number of limitations on accepted memory values. For more information, see the GCP documentation (here.)[https://cloud.google.com/compute/docs/instances/creating-instance-with-custom-machine-type#specifications]
- preemptible\_percentage (Optional) Percentage of Preemptible VMs to spin up from the "desired\_capacity".
- on\_demand\_count (Optional) Number of regular VMs to launch in the group. The rest will be Preemptible VMs. When this parameter is specified, the preemptible percentage parameter is being ignored.
- fallback\_to\_od (Optional) Activate fallback-to-on-demand. When provisioning an instance, if no Preemptible market is available, fallback-to-on-demand will provision an On-Demand instance to maintain the group capacity.
- draining\_timeout (Optional) Time (seconds) the instance is allowed to run after it is detached from the group. This is to allow the instance time to drain all the current TCP connections before terminating it.
- metadata (Optional) Array of objects with key-value pairs.
- key (Optional) Metadata key.
- value (Optional) Metadata value.
- labels (Optional) Array of objects with key-value pairs.
- key (Optional) Labels key.
- value (Optional) Labels value.
- tags (Optional) Tags to mark created instances.

#### » GPU

- gpu (Optional) Defines the GPU configuration.
- type (Required) The type of GPU instance. Valid values: nvidia-tesla-v100, nvidia-tesla-p100, nvidia-tesla-k80.

• count - (Required) The number of GPUs. Must be 0, 2, 4, 6, 8.

Usage:

```
gpu = {
  count = 2
  type = "nvidia-tesla-p100"
}
```

### » Health Check

• health\_check\_grace\_period - (optional) Period of time (seconds) to wait for VM to reach healthiness before monitoring for unhealthiness.

```
health_check_grace_period = 100
```

#### » Backend Services

- backend\_services (Optional) Describes the backend service configurations.
- service\_name (Required) The name of the backend service.
- location\_type (Optional) Sets which location the backend services will be active. Valid values: regional, global.
- scheme (Optional) Use when location\_type is "regional". Set the traffic for the backend service to either between the instances in the vpc or to traffic from the internet. Valid values: INTERNAL, EXTERNAL.
- named\_port (Optional) Describes a named port and a list of ports.
- port\_name (Required) The name of the port.
- ports (Required) A list of ports.

```
backend_services_config = {[
    {
       service_name = "spotinst-elb-backend-service"
       locationType = "regional"
       scheme = "INTERNAL"
       ports = {
            port_name = "port-name"
            ports = [8000, 6000]
       }
    },
}
```

#### » Disks

- disks (Optional) Array of disks associated with this instance. Persistent disks must be created before you can assign them.
- auto\_delete (Optional) Specifies whether the disk will be auto-deleted when the instance is deleted.
- boot (Optional) Indicates that this is a boot disk. The virtual machine will use the first partition of the disk for its root filesystem.
- device\_name (Optional) Specifies a unique device name of your choice.
- interface (Optional, Default: SCSI) Specifies the disk interface to use for attaching this disk, which is either SCSI or NVME.
- mode (Optional, Default: READ\_WRITE) The mode in which to attach this disk, either READ\_WRITE or READ\_ONLY.
- source (Optional) Specifies a valid partial or full URL to an existing Persistent Disk resource. This field is only applicable for persistent disks.
- type (Optional, Default: PERSISTENT) Specifies the type of disk, either SCRATCH or PERSISTENT.
- initialize\_params (Optional) Specifies the parameters for a new disk that will be created alongside the new instance. Use initialization parameters to create boot disks or local SSDs attached to the new instance.
- disk\_size\_gb (Optional) Specifies disk size in gigabytes. Must be in increments of 2.
- disk\_type (Optional, Default" pd-standard) Specifies the disk type to use to create the instance. Valid values: pd-ssd, local-ssd.
- source\_image (Optional) A source image used to create the disk. You can provide a private (custom) image, and Compute Engine will use the corresponding image from your project.

Usage:

```
disks = [
    {
      device_nime = "device"
                  = "READ_WRITE"
                  = "PERSISTENT"
      type
      auto_delete = true
      boot
                  = true
      interface
                  = "SCSI"
      initialize_parms = {
        disk_size_gb = 10
                     = "pd-standard"
        disk_type
        source_image = ""
      }
    }
 ]
```

#### » Network Interfaces

Each of the network\_interface attributes controls a portion of the GCP Instance's "Network Interfaces". It's a good idea to familiarize yourself with GCP's Network Interfaces does to understand the implications of using these attributes.

- network\_interface (Required, minimum 1) Array of objects representing the network configuration for the elastigroup.
- network (Required) Network resource for this group.
- access\_configs (Optional) Array of configurations.
- name (Optional) Name of this access configuration.
- type (Optional) Array of configurations for this interface. Currently, only ONE\_TO\_ONE\_NAT is supported.

```
network_interface = [{
  network = "default"

access_configs = {
    name = "config1"
    type = "ONE_TO_ONE_NAT"
  }

alias_ip_ranges = {
  subnetwork_range_name = "range-name-1"
  ip_cidr_range = "10.128.0.0/20"
  }
}]
```

#### » Scaling Policies

- scaling\_up\_policy (Optional) Contains scaling policies for scaling the Elastigroup up.
- scaling\_down\_policy (Optional) Contains scaling policies for scaling the Elastigroup down.

Each scaling\_\*\_policy supports the following:

- policy\_name (Optional) Name of scaling policy.
- metric\_name (Optional) Metric to monitor. Valid values: "Percentage CPU", "Network In", "Network Out", "Disk Read Bytes", "Disk Write Bytes", "Disk Write Operations/Sec", "Disk Read Operations/Sec".
- statistic (Optional) Statistic by which to evaluate the selected metric. Valid values: "AVERAGE", "SAMPLE\_COUNT", "SUM", "MINIMUM", "MAXIMUM", "PERCENTILE", "COUNT".
- threshold (Optional) The value at which the scaling action is triggered.
- period (Optional) Amount of time (seconds) for which the threshold must be met in order to trigger the scaling action.

- evaluation\_periods (Optional) Number of consecutive periods in which the threshold must be met in order to trigger a scaling action.
- cooldown (Optional) Time (seconds) to wait after a scaling action before resuming monitoring.
- operator (Optional) The operator used to evaluate the threshold against the current metric value. Valid values: "gt" (greater than), "get" (greater than or equal), "lt" (less than), "lte" (less than or equal).
- action (Optional) Scaling action to take when the policy is triggered.
- type (Optional) Type of scaling action to take when the scaling policy is triggered. Valid values: "adjustment", "setMinTarget", "updateCapacity", "percentageAdjustment"
- adjustment (Optional) Value to which the action type will be adjusted. Required if using "numeric" or "percentageAdjustment" action types.

#### Usage:

```
scaling = {
   up = {
     policy_name = "scale_up_1"
                = "stackdriver"
      source
     metric_name = "instance/disk/read_ops_count"
     namespace
                = "compute"
      statistic
                 = "average"
                  = "percent"
      unit
                  = 10000
      threshold
     period
                  = 300
      cooldown
                  = 300
                  = "gte"
      operator
      evaluation_periods = 1
      action = {
                   = "adjustment"
        type
        adjustment = 1
      dimensions = [
          name = "storage_type"
          value = "pd-ssd"
     ]
   }
```

### » Third-Party Integrations

- integration\_docker\_swarm (Optional) Describes the Docker Swarm integration.
  - master\_host (Required) IP or FQDN of one of your swarm managers.
  - master\_port (Required) Network port used by your swarm.

#### Usage:

```
integration_docker_swarm = {
    master_host = "10.10.10.10"
    master_port = 2376
}
```

# » spotinst\_elastigroup\_gke

Provides a Spotinst elastigroup GKE resource.

# » Example Usage

```
resource "spotinst_elastigroup_gke" "example_gke_group" {
   name = "example-gke"

   cluster_zone_name = "us-central1-a"
   cluster_id = "example-cluster"
   node_image = "COS"

   instance_types_ondemand = "n1-standard-1"
   instance_types_preemptible = ["n1-standard-1"]

   min_size = 0
   max_size = 3
   desired_capacity = 1
   preemptible_percentage = 75
}
```

# » Argument Reference

The following arguments are supported:

• name - (Optional) The group name.

- max\_size (Required) The maximum number of instances the group should have at any time.
- min\_size (Required) The minimum number of instances the group should have at any time.
- desired\_capacity (Required) The desired number of instances the group should have at any time.
- availability\_zones (Optional) List of availability zones for the group.
- cluster\_zone\_name (Required) The zone where the cluster is hosted.
- cluster\_id (Required) The name of the GKE cluster you wish to import.
- node\_image (Optional, Default: COS) The image that will be used for the node VMs. Possible values: COS, UBUNTU.
- preemptible\_percentage (Optional) The percentage of preemptible VMs that would spin up from the desired capacity (range: 0-100).
- instance\_types\_preemptible (Optional) The preemptible VMs instance type. To maximize cost savings and market availability, select as many types as possible. Required if instance\_types\_on\_demand is not set.
- instance\_types\_on\_demand (Optional) The regular VM instance type to use for mixed-type groups and when falling back to on-demand. Required if instance\_types\_preemptible is not set.

# » spotinst\_mrscaler

Provides a Spotinst AWS MrScaler resource.

#### » Example Usage - New Strategy

# Create a Mr Scaler with New strategy

```
= 15
   timeout
   timeout_action = "terminate"
// --- CLUSTER -----
                = "s3://example-logs"
 log_uri
 additional_info = "{'test':'more information'}"
  job_flow_role = "EMR_EC2_ExampleRole"
 security_config = "example-config"
               = "example-role"
 service_role
 visible_to_all_users = true
 termination_protected = false
 keep_job_flow_alive = true
// -----
// --- OPTONAL COMPUTE ----
  custom_ami_id = "ami-123456"
 repo_upgrade_on_boot = "NONE"
                    = "test-key"
 ec2_key_name
 managed_primary_security_group = "sg-123456"
 managed_replica_security_group = "sg-987654"
 service_access_security_group = "access-example"
 additional_primary_security_groups = ["sg-456321"]
 additional_replica_security_groups = ["sg-123654"]
  applications = [
   {
     name = "Ganglia"
     version = "1.0"
   },
   {
     name = "Hadoop"
   },
     name = "Pig"
     args = ["fake", "args"]
   }
 ]
 steps_file = {
   bucket = "example-bucket"
   key = "steps.json"
 }
```

```
configurations_file = {
   bucket = "example-bucket"
   key = "configurations.json"
 bootstrap_actions_file = {
   bucket = "terraform-emr-test"
   key = "bootstrap-actions.json"
// -----
// --- MASTER GROUP -----
 master_instance_types = ["c3.xlarge"]
 master_lifecycle = "SPOT"
 master_ebs_optimized = true
 master_ebs_block_device = {
   volumes_per_instance = 1
   volume_type = "gp2"
size in gb = 30
                    = 30
   size_in_gb
// -----
// --- CORE GROUP -----
 core_instance_types = ["c3.xlarge", "c4.xlarge"]
 core_min_size = 1
 core_max_size
                = 1
 core_desired_capacity = 1
 core_lifecycle = "ON_DEMAND"
 core_ebs_optimized = false
 core_ebs_block_device = {
   volumes_per_instance = 2
   volume_type = "gp2"
                    = 40
   size_in_gb
// -----
// --- TASK GROUP -----
 task_instance_types = ["c3.xlarge", "c4.xlarge"]
 task_min_size = 0
                   = 30
 task_max_size
 task_desired_capacity = 1
 task_lifecycle = "SPOT"
 task_ebs_optimized = false
```

```
task_ebs_block_device = {
   volumes_per_instance = 2
                     = "gp2"
   volume_type
   size_in_gb
                      = 40
// -----
// --- TAGS -----
 tags = [{
     key = "Creator"
     value = "Terraform"
 }]
// -----
» Example Usage - Clone Strategy
# Create a Mr Scaler with Clone strategy and Task scaling
output "mrscaler-name" {
 value = "${spotinst_mrscaler_aws.Terraform-MrScaler-01.name}"
output "mrscaler-created-cluster-id" {
 value = "${spotinst_mrscaler_aws.Terraform-MrScaler-01.output_cluster_id}"
resource "spotinst_mrscaler_aws" "Terraform-MrScaler-01" {
          = "Terraform-MrScaler-01"
 description = "Testing MrScaler creation via Terraform"
 region = "us-west-2"
          = "clone"
 strategy
                = "j-123456789"
 cluster_id
 expose_cluster_id = true
 availability_zones = ["us-west-2a:subnet-12345678"]
// --- MASTER GROUP -----
 master_instance_types = ["c3.xlarge"]
 master_lifecycle = "SPOT"
 master_ebs_optimized = true
 master_ebs_block_device = {
   volumes_per_instance = 1
```

```
// --- CORE GROUP -----
 core_instance_types = ["c3.xlarge", "c4.xlarge"]
 core_min_size = 1
core_max_size = 1
 core_desired_capacity = 1
 core_lifecycle = "ON_DEMAND"
 core_ebs_optimized = false
 core ebs block device = {
   volumes_per_instance = 2
   size_in_gb
// -----
// --- TASK GROUP -----
 task_instance_types = ["c3.xlarge", "c4.xlarge"]
 task_min_size = 0
task_max_size = 30
 task_desired_capacity = 1
 task_lifecycle = "SPOT"
 task_ebs_optimized = false
 task_ebs_block_device = {
   volumes_per_instance = 2
   volume_type = "gp2"
   size_in_gb
 }
// -----
// --- TAGS -----
 tags = [{
    key = "Creator"
    value = "Terraform"
 }]
// -----
// --- TASK SCALING POLICY -----
 task_scaling_down_policy = [{
   policy_name = "policy-name"
   metric_name = "CPUUtilization"
```

```
namespace = "AWS/EC2"
   statistic = "average"
   unit = ""
   threshold = 10
   adjustment = "1"
   cooldown = 60
   dimensions = {
     name = "name-1"
     value = "value-1"
   }
             = "gt"
   operator
   evaluation_periods = 10
   period
                   = 60
   action_type = ""
   minimum = 0
   maximum = 10
            = 5
   target
   max_target_capacity = 1
» Example Usage - Wrap Strategy
# Create a Mr Scaler with Wrap strategy
resource "spotinst_mrscaler" "example-scaler-2" {
 name = "spotinst-mr-scaler-2"
 description = "created by Terraform"
 region = "us-west-2"
 strategy = "wrap"
 cluster_id = "j-27UVDEHXL40QM"
// --- TASK GROUP -----
 task_instance_types = ["c3.xlarge","c4.xlarge"]
 task_target
               = 2
 task_minimum = 0
 task_maximum = 4
 task_lifecycle = "SPOT"
 task_ebs_block_device = {
   volumes_per_instance = 1
```

volume\_type = "gp2"

The following arguments are supported:

- name (Required) The MrScaler name.
- description (Optional) The MrScaler description.
- region (Required) The MrScaler region.
- strategy (Required) The MrScaler strategy. Allowed values are new clone and wrap.
- cluster\_id (Optional) The MrScaler cluster id.
- expose\_cluster\_id (Optional) Allow the cluster\_id to set a Terraform output variable.

# » Provisioning Timeout (Clone, New strategies)

- timeout (Optional) The amount of time (minutes) after which the cluster is automatically terminated if it's still in provisioning status. Minimum: '15'.
- timeout\_action (Optional) The action to take if the timeout is exceeded. Valid values: terminate, terminateAndRetry.

### » Cluster Configuration (New strategy only)

- log\_uri (Optional) The path to the Amazon S3 location where logs for this cluster are stored.
- additional\_info (Optional) This is meta information about third-party applications that third-party vendors use for testing purposes.
- security\_config (Optional) The name of the security configuration applied to the cluster.
- service\_role (Optional) The IAM role that will be assumed by the Amazon EMR service to access AWS resources on your behalf.
- job\_flow\_role (Optional) The IAM role that was specified when the job flow was launched. The EC2 instances of the job flow assume this role.
- visible\_to\_all\_users (Optional) Specifies whether the cluster is visible to all IAM users of the AWS account associated with the cluster.
- termination\_protected (Optional) Specifies whether the Amazon EC2 instances in the cluster are protected from termination by API calls, user intervention, or in the event of a job-flow error.

• keep\_job\_flow\_alive - (Optional) Specifies whether the cluster should remain available after completing all steps.

### » Task Group (Wrap, Clone, and New strategies)

- task\_instance\_types (Required) The MrScaler instance types for the task nodes.
- task\_target (Required) amount of instances in task group.
- task\_maximum (Optional) maximal amount of instances in task group.
- task\_minimum (Optional) The minimal amount of instances in task group.
- task\_lifecycle (Required) The MrScaler lifecycle for instances in task group. Allowed values are 'SPOT' and 'ON\_DEMAND'.
- task\_ebs\_optimized (Optional) EBS Optimization setting for instances in group.
- task\_ebs\_block\_device (Required) This determines the ebs configuration for your task group instances. Only a single block is allowed.
  - volumes\_per\_instance (Optional; Default 1) Amount of volumes per instance in the task group.
  - volume\_type (Required) volume type. Allowed values are 'gp2',
     'io1' and others.
  - size\_in\_gb (Required) Size of the volume, in GBs.
  - iops (Optional) IOPS for the volume. Required in some volume types, such as io1.

### » Core Group (Clone, New strategies)

- core\_instance\_types (Required) The MrScaler instance types for the core nodes.
- core target (Required) amount of instances in core group.
- core\_maximum (Optional) maximal amount of instances in core group.
- core\_minimum (Optional) The minimal amount of instances in core group.
- core\_lifecycle (Required) The MrScaler lifecycle for instances in core group. Allowed values are 'SPOT' and 'ON\_DEMAND'.
- core\_ebs\_optimized (Optional) EBS Optimization setting for instances in group.
- core\_ebs\_block\_device (Required) This determines the ebs configuration for your core group instances. Only a single block is allowed.
  - volumes\_per\_instance (Optional; Default 1) Amount of volumes per instance in the core group.
  - volume\_type (Required) volume type. Allowed values are 'gp2',
     'io1' and others.
  - size\_in\_gb (Required) Size of the volume, in GBs.

 iops - (Optional) IOPS for the volume. Required in some volume types, such as io1.

### » Master Group (Clone, New strategies)

- master\_instance\_types (Required) The MrScaler instance types for the master nodes.
- master\_lifecycle (Required) The MrScaler lifecycle for instances in master group. Allowed values are 'SPOT' and 'ON DEMAND'.
- master\_ebs\_optimized (Optional) EBS Optimization setting for instances in group.
- master\_ebs\_block\_device (Required) This determines the ebs configuration for your master group instances. Only a single block is allowed.
  - volumes\_per\_instance (Optional; Default 1) Amount of volumes per instance in the master group.
  - volume\_type (Required) volume type. Allowed values are 'gp2', 'io1' and others.
  - size\_in\_gb (Required) Size of the volume, in GBs.
  - iops (Optional) IOPS for the volume. Required in some volume types, such as io1.

### » Tags (Clone, New strategies)

- tags (Optional) A list of tags to assign to the resource. You may define multiple tags.
  - key (Required) Tag key.
  - value (Required) Tag value.

## » Optional Compute Parameters (New strategy)

- managed\_primary\_security\_group (Optional) EMR Managed Security group that will be set to the primary instance group.
- managed\_replica\_security\_group (Optional) EMR Managed Security group that will be set to the replica instance group.
- service\_access\_security\_group (Optional) The identifier of the Amazon EC2 security group for the Amazon EMR service to access clusters in VPC private subnets.
- additional\_primary\_security\_groups (Optional) A list of additional Amazon EC2 security group IDs for the master node.
- additional\_replica\_security\_groups (Optional) A list of additional Amazon EC2 security group IDs for the core and task nodes.
- custom\_ami\_id (Optional) The ID of a custom Amazon EBS-backed Linux AMI if the cluster uses a custom AMI.

- repo\_upgrade\_on\_boot (Optional) Applies only when custom\_ami\_id is used. Specifies the type of updates that are applied from the Amazon Linux AMI package repositories when an instance boots using the AMI. Possible values include: SECURITY, NONE.
- ec2\_key\_name (Optional) The name of an Amazon EC2 key pair that can be used to ssh to the master node.
- applications (Optional) A case-insensitive list of applications for Amazon EMR to install and configure when launching the cluster
  - args (Optional) Arguments for EMR to pass to the application.
  - name (Required) The application name.
  - version- (Optional)T he version of the application.

### » Availability Zones (Clone, New strategies)

• availability\_zones - (Required in Clone) List of AZs and their subnet Ids. See example above for usage.

#### » Configurations (Clone, New strategies)

- configurations\_file (Optional) Describes path to S3 file containing description of configurations. More Information
  - bucket (Required) S3 Bucket name for configurations.
  - key- (Required) S3 key for configurations.

#### » Steps (Clone, New strategies)

- steps\_file (Optional) Steps from S3.
  - bucket (Required) S3 Bucket name for steps.
  - key- (Required) S3 key for steps.

#### » Bootstrap Actions (Clone, New strategies)

- bootstrap\_actions\_file (Optional) Describes path to S3 file containing description of bootstrap actions. More Information
  - bucket (Required) S3 Bucket name for bootstrap actions.
  - key- (Required) S3 key for bootstrap actions.

#### » Scaling Policies

Possible task group scaling policies (Wrap, Clone, and New strategies): \*task\_scaling\_up\_policy \*task\_scaling\_down\_policy

Possible core group scaling policies (Clone, New strategies): \* core\_scaling\_up\_policy \* core\_scaling\_down\_policy

Each \*\_scaling\_\*\_policy supports the following:

- policy\_name (Required) The name of the policy.
- metric\_name (Required) The name of the metric, with or without spaces.
- statistic (Required) The metric statistics to return. For information about specific statistics go to Statistics in the Amazon CloudWatch Developer Guide.
- unit (Required) The unit for the metric.
- threshold (Required) The value against which the specified statistic is compared.
- adjustment (Optional) The number of instances to add/remove to/from the target capacity when scale is needed.
- min\_target\_capacity (Optional) Min target capacity for scale up.
- max\_target\_capacity (Optional) Max target capacity for scale down.
- namespace (Required) The namespace for the metric.
- operator (Required) The operator to use. Allowed values are : 'gt', 'gte', 'lt', 'lte'.
- evaluation\_periods (Required) The number of periods over which data is compared to the specified threshold.
- period (Required) The granularity, in seconds, of the returned datapoints. Period must be at least 60 seconds and must be a multiple of 60.
- cooldown (Required) The amount of time, in seconds, after a scaling activity completes and before the next scaling activity can start.
- dimensions (Optional) A mapping of dimensions describing qualities of the metric.
- minimum (Optional) The minimum to set when scale is needed.
- maximum (Optional) The maximum to set when scale is needed.
- target (Optional) The number of instances to set when scale is needed.
- action\_type (Required) The type of action to perform. Allowed values are : 'adjustment', 'setMinTarget', 'setMaxTarget', 'updateCapacity', 'percentageAdjustment'

#### » Scheduled Tasks

- scheduled\_task (Optional) An array of scheduled tasks.
- is\_enabled (Optional) Enable/Disable the specified scheduling task.
- task\_type (Required) The type of task to be scheduled. Valid values: setCapacity.
- instance\_group\_type (Required) Select the EMR instance groups to execute the scheduled task on. Valid values: task.
- cron (Required) A cron expression representing the schedule for the task.
- desired\_capacity (Optional) New desired capacity for the elastigroup.

- min\_capacity (Optional) New min capacity for the elastigroup.
- max\_capacity (Optional) New max capacity for the elastigroup.

#### » Attributes Reference

The following attributes are exported:

• id - The scaler ID.

# » spotinst\_multai\_balancer

Provides a Spotinst Multai Balancer.

# » Example Usage

```
resource "multai_balancer" "my_balancer" {
  name = "foo"
  scheme = "internal"

connection_timeouts = {
  idle = 10
  draining = 10
 }

tags = [{
  key = "env"
  value = "prod"
 }]
}
```

## » Argument Reference

The following arguments are supported:

- name (Required) The balancer name. May contain only alphanumeric characters or hyphens, and must not begin or end with a hyphen.
- scheme (Optional)
- dns\_cname\_aliases (Optional)
- connection\_timeouts (Optional)
- idle (Optional) The idle timeout value, in seconds. (range: 1 3600).

- draining (Optional) The time for the load balancer to keep connections alive before reporting the target as de-registered, in seconds (range: 1 3600).
- tags (Optional) A list of key:value paired tags.
- key (Required) The tag's key.
- value (Required) The tag's value.

# » spotinst\_multai\_deployment

Provides a Spotinst Multai Deployment.

## » Example Usage

```
resource "multai_deployment" "my_deployment" {
  name = "foo"
}
```

### » Argument Reference

The following arguments are supported:

• name - (Required) The deployment name.

# » spotinst\_multai\_listener

Provides a Spotinst Multai Listener.

```
}
tags = [{
   key = "env"
   value = "prod"
}]
```

The following arguments are supported:

- balancer\_id (Required) The ID of the balancer.
- protocol (Required) The protocol to allow connections to the load balancer.
- port (Required) The port on which the load balancer is listening.
- tls\_config (Optional) Describes the TLSConfig configuration.
- min\_version (Required) MinVersion contains the minimum SSL/TLS version that is acceptable (1.0 is the minimum)
- max\_version (Required) MaxVersion contains the maximum SSL/TLS version that is acceptable. \*
- tags (Optional) A list of key:value paired tags.
- key (Required) The tag's key.
- value (Required) The tag's value.

# » spotinst\_multai\_routing\_rule

Provides a Spotinst Multai Routing Rule.

```
resource "multai_routing_rule" "my_routing_rule" {
  balancer_id = "b-12345"
  listener_id = "l-98765"
  route = "Path(\x60/bar\x60)"
  strategy = "LEASTCONN"

tags = [{
   key = "env"
```

```
value = "prod"
}]
```

The following arguments are supported:

- balancer\_id (Required) The ID of the balancer.
- listener\_id (Required) The ID of the listener.
- route (Required) Route defines a simple language for matching HTTP requests and route the traffic accordingly. Route provides series of matchers that follow the syntax: Path matcher: Path("/foo/bar") // trie-based PathRegexp("/foo/.") // regexp-based Method matcher: Method("GET") // trie-based MethodRegexp("POST|PUT") // regexp based Header matcher: Header("Content-Type", "application/json") // trie-based HeaderRegexp("Content-Type", "application/.") // regexp based Matchers can be combined using && operator: Method("POST") && Path("/v1")
- strategy (Optional) Balancing strategy. Valid values: ROUNDROBIN, RANDOM, LEASTCONN, IPHASH.
- tags (Optional) A list of key:value paired tags.
- key (Required) The tag's key.
- value (Required) The tag's value.

# » spotinst\_multai\_target

Provides a Spotinst Multai Target.

```
resource "multai_target" "my_target" {
  balancer_id = "b-12345"
  target_set_id = "l-98765"

name = "foo"
  port = 1338
  host = "host"
  weight = 1
```

```
tags = [{
    key = "env"
    value = "prod"
}]
```

The following arguments are supported:

- balancer\_id (Required) The ID of the balancer.
- target\_set\_id (Required) The ID of the target set.
- name (Required) The name of the Target. Must contain only alphanumeric characters or hyphens, and must not begin or end with a hyphen.
- port (Required) The port the target will register to.
- host (Required) The address (IP or URL) of the targets to register
- weight (Required) Defines how traffic is distributed between targets.
- tags (Optional) A list of key:value paired tags.
- key (Required) The tag's key.
- value (Required) The tag's value.

# » spotinst\_multai\_target\_set

Provides a Spotinst Multai Target Set.

```
resource "multai_target_set" "my_target_set" {
  balancer_id = "b-12345"
 deployment_id = "dp-12345"
              = "foo"
 name
               = "http"
 protocol
               = 1338
 port
 weight
 health_check = {
   protocol = "http"
            = "/"
    path
   port
            = 3001
```

```
interval = 20
timeout = 5

healthy_threshold = 3
unhealthy_threshold = 3
}

tags = [{
key = "env"
value = "prod"
}]
```

The following arguments are supported:

- name (Required) The name of the Target Set. Must contain only alphanumeric characters or hyphens, and must not begin or end with a hyphen.
- balancer\_id (Required) The id of the balancer.
- deployment\_id (Required) The id of the deployment.
- protocol (Required) The protocol to allow connections to the target.
- port
- weight (Required) Defines how traffic is distributed between the Target Set.
- health check
- protocol (Required) The protocol to allow connections to the target for the health check.
- path (Required) The path to perform the health check.
- port (Required) The port on which the load balancer is listening.
- interval (Required) The interval for the health check.
- timeout (Required) The time out for the health check.
- healthy\_threshold (Required) Total number of allowed healthy Targets.
- unhealthy\_threshold (Required) Total number of allowed unhealthy Targets.
- tags (Optional) A list of key:value paired tags.

- key (Required) The tag's key.
- value (Required) The tag's value.

# » spotinst\_ocean\_aws

Provides a Spotinst Ocean AWS resource.

```
resource "spotinst_ocean_aws" "example" {
 name = "demo"
 controller id = "fakeClusterId"
 region = "us-west-2"
 max_size
                  = 2
                 = 1
 min_size
 desired_capacity = 2
 subnet_ids = ["subnet-123456789"]
 whitelist = ["t1.micro", "m1.small"]
 // --- LAUNCH CONFIGURATION -----
             = "ami-123456"
 image_lu
security_groups = L"sg-90100
= "fake key"
 image_id
                    = ["sg-987654321"]
                      = "echo hello world"
 user_data
 iam_instance_profile = "iam-profile"
 associate_public_ip_address = true
 load_balancers = [
   {
     arn = "arn:aws:elasticloadbalancing:us-west-2:fake-arn"
     type = "TARGET_GROUP"
   },
   {
     name = "AntonK"
     type = "CLASSIC"
 ]
 // --- STRATEGY -----
 fallback_to_ondemand
                         = true
  spot_percentage
                            = 100
```

```
utilize_reserved_instances = false
  // --- AUTOSCALER -----
  autoscaler = {
   autoscale_is_enabled
                          = false
   autoscale_is_auto_config = false
                       = 300
   autoscale_cooldown
   autoscale_headroom = {
     cpu_per_unit
                   = 1024
     gpu_per_unit
     memory_per_unit = 512
     num of units
   }
   autoscale_down = {
     evaluation_periods = 300
   resource_limits = {
     max_vcpu = 1024
     max_memory_gib = 20
 }
}
```

The following arguments are supported:

- name (Required) The cluster name.
- controller\_id (Required) The ocean cluster identifier. Example: ocean.k8s
- region (Required) The region the cluster will run in.
- max\_size (Optional, Default: 1000) The upper limit of instances the cluster can scale up to.
- min\_size (Optional) The lower limit of instances the cluster can scale down to.
- desired\_capacity (Optional) The number of instances to launch and maintain in the cluster.
- subnet\_ids (Required) A comma-separated list of subnet identifiers for the Ocean cluster. Subnet IDs should be configured with auto assign public ip.

- whitelist (Optional) Instance types allowed in the Ocean cluster. Cannot be configured if blacklist is configured.
- blacklist (Optional) Instance types not allowed in the Ocean cluster. Cannot be configured if whitelist is configured.

```
whitelist = ["t1.micro", "m1.small"]
// blacklist = ["t1.micro", "m1.small"]
```

- user\_data (Optional) Base64-encoded MIME user data to make available to the instances.
- image\_id (Required) ID of the image used to launch the instances.
- security\_groups (Required) One or more security group ids.
- key\_name (Optional) The key pair to attach the instances.
- iam\_instance\_profile (Optional) The instance profile iam role.
- associate\_public\_ip\_address (Optional)
- load\_balancers (Optional) Array of load balancer objects to add to ocean cluster
  - arn (Optional) Required if type is set to TARGET\_GROUP
  - name (Optional) Required if type is set to CLASSIC
  - type (Required) Can be set to CLASSIC or TARGET\_GROUP

```
= "ami-79826301"
image_id
                     = ["sg-042d658b3ee907848"]
security_groups
                     = "fake key"
key_name
user_data
                     = "echo hello world"
iam_instance_profile = "iam-profile"
associate_public_ip_address = true
load_balancers = [
    arn = "arn:aws:elasticloadbalancing:us-west-2:fake-arn"
    type = "TARGET_GROUP"
  },
    name = "AntonK"
    type = "CLASSIC"
  }
]
```

• fallback\_to\_ondemand - (Optional, Default: true) If not Spot instance markets are available, enable Ocean to launch On-Demand instances in-

stead.

- spot\_percentage (Optional, Default: 100) The percentage of Spot instances the cluster should maintain. Min 0, max 100.
- utilize\_reserved\_instances (Optional, Default false) If Reserved instances exist, OCean will utilize them before launching Spot instances.

```
fallback_to_ondemand = true
spot_percentage = 100
utilize reserved instances = false
```

- autoscaler (Optional) Describes the Ocean Kubernetes autoscaler.
- autoscale\_is\_enabled (Optional, Default: true) Enable the Ocean Kubernetes autoscaler.
- autoscale\_is\_auto\_config (Optional, Default: true) Automatically configure and optimize headroom resources.
- autoscale\_cooldown (Optional, Default: null) Cooldown period between scaling actions.
- autoscale\_headroom (Optional) Spare resource capacity management enabling fast assignment of Pods without waiting for new resources to launch.
- cpu\_per\_unit (Optional) Optionally configure the number of CPUs to allocate the headroom. CPUs are denoted in millicores, where 1000 millicores = 1 vCPU.
- gpu\_per\_unit (Optional) Optionally configure the number of GPUS to allocate the headroom.
- memory\_per\_unit (Optional) Optionally configure the amount of memory (MB) to allocate the headroom.
- num\_of\_units (Optional) The number of units to retain as headroom, where each unit has the defined headroom CPU and memory.
- autoscale\_down (Optional) Auto Scaling scale down operations.
- evaluation\_periods (Optional, Default: null) The number of evaluation periods that should accumulate before a scale down action takes place.
- resource\_limits (Optional) Optionally set upper and lower bounds on the resource usage of the cluster.
- max\_vcpu (Optional) The maximum cpu in vCPU units that can be allocated to the cluster.
- max\_memory\_gib (Optional) The maximum memory in GiB units that can be allocated to the cluster.

```
autoscaler = {
  autoscale_is_enabled = false
  autoscale_is_auto_config = false
  autoscale_cooldown = 300

autoscale_headroom = {
   cpu_per_unit = 1024
```

```
gpu_per_unit
      memory_per_unit = 512
      num_of_units
    }
    autoscale_down = {
      evaluation_periods = 300
    }
    resource_limits = {
      max_vcpu = 1024
      max_memory_gib = 20
    }
 }
  • tags - (Optional) Optionally adds tags to instances launched in an Ocean
     cluster.
  • key - (Optional) The tag key.
  • value - (Optional) The tag value.
tags = [{
 key = "fakeKey"
  value = "fakeValue"
}]
```

# » spotinst\_subscription

Provides a Spotinst subscription resource.

```
# Create a Subscription
resource "spotinst_subscription" "default-subscription" {
    resource_id = "${spotinst_elastigroup_aws.my-eg.id}"
    event_type = "AWS_EC2_INSTANCE_LAUNCH"
    protocol = "http"
    endpoint = "http://endpoint.com"

format = {
    event = "%event%"
    instance_id = "%instance-id%"
    resource_id = "%resource-id%"
    resource_name = "%resource-name%"
```

```
tags = "foo,baz,baz"
}
```

The following arguments are supported:

- resource\_id (Required) Spotinst Resource ID (Elastigroup ID).
- event\_type (Required) The event to send the notification when triggered.

  Valid values: "AWS\_EC2\_INSTANCE\_TERMINATE", "AWS\_EC2\_INSTANCE\_TERMINATED",

  "AWS\_EC2\_INSTANCE\_LAUNCH", "AWS\_EC2\_INSTANCE\_UNHEALTHY\_IN\_ELB",

  "GROUP\_ROLL\_FAILED", "GROUP\_ROLL\_FINISHED", "CANT\_SCALE\_UP\_GROUP\_MAX\_CAPACITY",

  "GROUP\_UPDATED", "AWS\_EC2\_CANT\_SPIN\_OD", "AWS\_EMR\_PROVISION\_TIMEOUT",

  "AWS\_EC2\_INSTANCE\_READY\_SIGNAL\_TIMEOUT".
- protocol (Required) The protocol to send the notification. Valid values: "http", "https", "email", "email-json", "aws-sns", "web".
- endpoint (Required) The endpoint the notification will be sent to: url in case of "http"/"https", email address in case of "email"/"email-json", sns-topic-arn in case of "aws-sns".
- format (Optional) The format of the notification content (JSON Format Key+Value). Valid values: "%instance-id%", "%event%", "%resource-id%", "%resource-name%".

#### » Attributes Reference

The following attributes are exported:

• id - The subscription ID.