## » openstack\_blockstorage\_availability\_zones\_v3

Use this data source to get a list of Block Storage availability zones from Open-Stack

## » Example Usage

```
data "openstack_blockstorage_availability_zones_v3" "zones" {}
```

### » Argument Reference

- region (Optional) The region in which to obtain the Block Storage client. If omitted, the region argument of the provider is used.
- state (Optional) The state of the availability zones to match. Can either be available or unavailable. Default is available.

#### » Attributes Reference

id is set to hash of the returned zone list. In addition, the following attributes are exported:

- region See Argument Reference above.
- state See Argument Reference above.
- names The names of the availability zones, ordered alphanumerically, that match the queried state.

# $\verb|w openstack_blockstorage_snapshot_v2|\\$

Use this data source to get information about an existing snapshot.

- region (Optional) The region in which to obtain the V2 Block Storage client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the snapshot.
- status (Optional) The status of the snapshot.
- volume\_id (Optional) The ID of the snapshot's volume.
- most\_recent (Optional) Pick the most recently created snapshot if there are multiple results.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- status See Argument Reference above.
- volume\_id See Argument Reference above.
- description The snapshot's description.
- size The size of the snapshot.
- metadata The snapshot's metadata.

# 

Use this data source to get information about an existing snapshot.

#### » Example Usage

- region (Optional) The region in which to obtain the V3 Block Storage client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the snapshot.
- status (Optional) The status of the snapshot.

- volume\_id (Optional) The ID of the snapshot's volume.
- most\_recent (Optional) Pick the most recently created snapshot if there are multiple results.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- status See Argument Reference above.
- volume\_id See Argument Reference above.
- description The snapshot's description.
- size The size of the snapshot.
- metadata The snapshot's metadata.

# » openstack\_blockstorage\_volume\_v2

Use this data source to get information about an existing volume.

## » Example Usage

```
data "openstack_blockstorage_volume_v2" "volume_1" {
  name = "volume_1"
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Block Storage client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the volume.
- status (Optional) The status of the volume.
- metadata (Optional) Metadata key/value pairs associated with the volume.

## » Attributes Reference

id is set to the ID of the found volume. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- status See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type The type of the volume.
- bootable Indicates if the volume is bootable.
- size The size of the volume in GBs.
- source\_volume\_id The ID of the volume from which the current volume was created.

## » openstack blockstorage volume v3

Use this data source to get information about an existing volume.

## » Example Usage

```
data "openstack_blockstorage_volume_v3" "volume_1" {
  name = "volume_1"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V3 Block Storage client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the volume.
- status (Optional) The status of the volume.
- metadata (Optional) Metadata key/value pairs associated with the volume.

#### » Attributes Reference

id is set to the ID of the found volume. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- status See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type The type of the volume.
- bootable Indicates if the volume is bootable.

- size The size of the volume in GBs.
- source\_volume\_id The ID of the volume from which the current volume was created.
- multiattach Indicates if the volume can be attached to more then one server.

# » openstack\_compute\_availability\_zones\_v2

Use this data source to get a list of availability zones from OpenStack

## » Example Usage

```
data "openstack_compute_availability_zones_v2" "zones" {}
```

## » Argument Reference

- region (Optional) The region to fetch availability zones from, defaults to the provider's region
- state (Optional) The state of the availability zones to match, default ("available").

### » Attributes Reference

id is set to hash of the returned zone list. In addition, the following attributes are exported:

• names - The names of the availability zones, ordered alphanumerically, that match the queried state

# ightarrow openstack\_compute\_flavor\_v2

Use this data source to get the ID of an available OpenStack flavor.

```
data "openstack_compute_flavor_v2" "small" {
  vcpus = 1
  ram = 512
}
```

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used.
- flavor\_id (Optional) The ID of the flavor. Conflicts with the name, min\_ram and min\_disk
- name (Optional) The name of the flavor. Conflicts with the flavor\_id.
- min\_ram (Optional) The minimum amount of RAM (in megabytes). Conflicts with the flavor\_id.
- ram (Optional) The exact amount of RAM (in megabytes).
- min\_disk (Optional) The minimum amount of disk (in gigabytes). Conflicts with the flavor\_id.
- disk (Optional) The exact amount of disk (in gigabytes).
- vcpus (Optional) The amount of VCPUs.
- swap (Optional) The amount of swap (in gigabytes).
- rx\_tx\_factor (Optional) The rx\_tx\_factor of the flavor.

#### » Attributes Reference

id is set to the ID of the found flavor. In addition, the following attributes are exported:

- extra\_specs Key/Value pairs of metadata for the flavor.
- is\_public Whether the flavor is public or private.

# 

Use this data source to get the ID and public key of an OpenStack keypair.

```
data "openstack_compute_keypair_v2" "kp" {
  name = "sand"
}
```

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used.
- name (Required) The unique name of the keypair.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- fingerprint The fingerprint of the OpenSSH key.
- public\_key The OpenSSH-formatted public key of the keypair.

## » openstack\_containerinfra\_cluster\_v1

Use this data source to get the ID of an available OpenStack Magnum cluster.

## » Example Usage

```
data "openstack_containerinfra_cluster_v1" "cluster_1" {
  name = "cluster_1"
}
```

#### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 Container Infra client. If omitted, the region argument of the provider is used.
- name (Required) The name of the cluster.

#### » Attributes Reference

id is set to the ID of the found cluster. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.

- project\_id The project of the cluster.
- user\_id The user of the cluster.
- created\_at The time at which cluster was created.
- updated\_at The time at which cluster was updated.
- api\_address COE API address.
- coe\_version COE software version.
- cluster\_template\_id The UUID of the V1 Container Infra cluster template.
- create\_timeout The timeout (in minutes) for creating the cluster.
- discovery url The URL used for cluster node discovery.
- docker\_volume\_size The size (in GB) of the Docker volume.
- flavor The flavor for the nodes of the cluster.
- master\_flavor The flavor for the master nodes.
- keypair The name of the Compute service SSH keypair.
- labels The list of key value pairs representing additional properties of the cluster.
- master\_count The number of master nodes for the cluster.
- node count The number of nodes for the cluster.
- fixed\_network The fixed network that is attached to the cluster.
- fixed\_subnet The fixed subnet that is attached to the cluster.
- master\_addresses IP addresses of the master node of the cluster.
- node addresses IP addresses of the node of the cluster.
- stack\_id UUID of the Orchestration service stack.

# » openstack\_containerinfra\_clustertemplate\_v1

Use this data source to get the ID of an available OpenStack Magnum cluster template.

### » Example Usage

data "openstack\_containerinfra\_clustertemplate\_v1" "clustertemplate\_1" {
 name = "clustertemplate\_1"

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 Container Infra client. If omitted, the region argument of the provider is used.
- name (Required) The name of the cluster template.

#### » Attributes Reference

id is set to the ID of the found cluster template. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- project\_id The project of the cluster template.
- user\_id The user of the cluster template.
- created\_at The time at which cluster template was created.
- updated\_at The time at which cluster template was updated.
- apiserver\_port The API server port for the Container Orchestration Engine for this cluster template.
- coe The Container Orchestration Engine for this cluster template.
- cluster\_distro The distro for the cluster (fedora-atomic, coreos, etc.).
- dns\_nameserver Address of the DNS nameserver that is used in nodes of the cluster.
- docker\_storage\_driver Docker storage driver. Changing this updates the Docker storage driver of the existing cluster template.
- docker\_volume\_size The size (in GB) of the Docker volume.
- external\_network\_id The ID of the external network that will be used for the cluster.
- fixed network The fixed network that will be attached to the cluster.
- fixed\_subnet = The fixed subnet that will be attached to the cluster.
- flavor The flavor for the nodes of the cluster.
- master\_flavor The flavor for the master nodes.

- floating\_ip\_enabled Indicates whether created cluster should create IP floating IP for every node or not.
- http\_proxy The address of a proxy for receiving all HTTP requests and relay them.
- https\_proxy The address of a proxy for receiving all HTTPS requests and relay them.
- image The reference to an image that is used for nodes of the cluster.
- insecure\_registry The insecure registry URL for the cluster template.
- keypair\_id The name of the Compute service SSH keypair.
- labels The list of key value pairs representing additional properties of the cluster template.
- master\_lb\_enabled Indicates whether created cluster should has a load-balancer for master nodes or not.
- network\_driver The name of the driver for the container network.
- no\_proxy A comma-separated list of IP addresses that shouldn't be used in the cluster.
- public Indicates whether cluster template should be public.
- registry\_enabled Indicates whether Docker registry is enabled in the cluster
- server type The server type for the cluster template.
- tls\_disabled Indicates whether the TLS should be disabled in the cluster.
- volume\_driver The name of the driver that is used for the volumes of the cluster nodes.

# ightarrow openstack\_dns\_zone\_v2

Use this data source to get the ID of an available OpenStack DNS zone.

```
data "openstack_dns_zone_v2" "zone_1" {
  name = "example.com"
}
```

- region (Optional) The region in which to obtain the V2 DNS client. A DNS client is needed to retrieve zone ids. If omitted, the region argument of the provider is used.
- name (Optional) The name of the zone.
- description (Optional) A description of the zone.
- email (Optional) The email contact for the zone record.
- status (Optional) The zone's status.
- ttl (Optional) The time to live (TTL) of the zone.
- type (Optional) The type of the zone. Can either be PRIMARY or SECONDARY.

#### » Attributes Reference

id is set to the ID of the found zone. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- email See Argument Reference above.
- type See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- status See Argument Reference above.
- attributes Attributes of the DNS Service scheduler.
- masters An array of master DNS servers. When type is SECONDARY.
- created\_at The time the zone was created.
- updated\_at The time the zone was last updated.
- transferred\_at The time the zone was transferred.
- version The version of the zone.
- serial The serial number of the zone.
- pool\_id The ID of the pool hosting the zone.
- project\_id The project ID that owns the zone.

# » openstack\_fw\_policy\_v1

Use this data source to get firewall policy information of an available OpenStack firewall policy.

## » Example Usage

```
data "openstack_fw_policy_v1" "policy" {
  name = "tf_test_policy"
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve firewall policy ids. If omitted, the region argument of the provider is used.
- policy\_id (Optional) The ID of the firewall policy.
- name (Optional) The name of the firewall policy.
- tenant\_id (Optional) The owner of the firewall policy.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- policy\_id See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- description The description of the firewall policy.
- audited The audit status of the firewall policy.
- shared The sharing status of the firewall policy.
- rules The array of one or more firewall rules that comprise the policy.

# » openstack\_identity\_auth\_scope\_v3

Use this data source to get authentication information about the current auth scope in use. This can be used as self-discovery or introspection of the username or project name currently in use.

```
data "openstack_identity_auth_scope_v3" "scope" {
  name = "my_scope"
}
```

- name (Required) The name of the scope. This is an arbitrary name which is only used as a unique identifier so an actual token isn't used as the ID.
- region (Optional) The region in which to obtain the V3 Identity client. A Identity client is needed to retrieve tokens IDs. If omitted, the region argument of the provider is used.

#### » Attributes Reference

id is set to the name given to the scope. In addition, the following attributes are exported:

- user\_name The username of the scope.
- user\_id The user ID the of the scope.
- user\_domain\_name The domain name of the user.
- user\_domain\_id The domain ID of the user.
- domain\_name The domain name of the scope.
- domain\_id The domain ID of the scope.
- project\_name The project name of the scope.
- project\_id The project ID of the scope.
- project\_domain\_name The domain name of the project.
- project\_domain\_id The domain ID of the project.
- roles A list of roles in the current scope. See reference below.

The roles block contains:

- role\_id The ID of the role.
- role\_name The name of the role.

# ${\tt "openstack\_identity\_endpoint\_v3"}$

Use this data source to get the ID of an OpenStack endpoint.

Note: This usually requires admin privileges.

```
data "openstack_identity_endpoint_v3" "endpoint_1" {
   service_name = "demo"
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the endpoint.
- endpoint\_region (Optional) The region the endpoint is assigned to. The region and endpoint\_region can be different.
- service\_id (Optional) The service id this endpoint belongs to.
- service\_name (Optional) The service name of the endpoint.
- service\_type (Optional) The service type of the endpoint.
- interface (Optional) The endpoint interface. Valid values are public, internal, and admin. Default value is public

#### » Attributes Reference

id is set to the ID of the found endpoint. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- endpoint\_region See Argument Reference above.
- service\_id See Argument Reference above.
- service\_name See Argument Reference above.
- service\_type See Argument Reference above.
- interface See Argument Reference above.
- url The endpoint URL.

# » openstack\_identity\_group\_v3

Use this data source to get the ID of an OpenStack group.

Note: This usually requires admin privileges.

```
data "openstack_identity_group_v3" "admins" {
  name = "admins"
}
```

- name The name of the group.
- domain\_id (Optional) The domain the group belongs to.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.

#### » Attributes Reference

id is set to the ID of the found group. In addition, the following attributes are exported:

- name See Argument Reference above.
- domain\_id See Argument Reference above.
- region See Argument Reference above.
- description A description of the group.

## » openstack\_identity\_project\_v3

Use this data source to get the ID of an OpenStack project.

## » Example Usage

```
data "openstack_identity_project_v3" "project_1" {
  name = "demo"
}
```

#### » Argument Reference

The following arguments are supported:

- domain\_id (Optional) The domain this project belongs to.
- enabled (Optional) Whether the project is enabled or disabled. Valid values are true and false.
- is\_domain (Optional) Whether this project is a domain. Valid values are true and false.
- name (Optional) The name of the project.
- parent\_id (Optional) The parent of this project.

id is set to the ID of the found project. In addition, the following attributes are exported:

- description The description of the project.
- domain\_id See Argument Reference above.
- enabled See Argument Reference above.
- is\_domain See Argument Reference above.
- name See Argument Reference above.
- parent\_id See Argument Reference above.
- region The region the project is located in.

# » openstack\_identity\_role\_v3

Use this data source to get the ID of an OpenStack role.

## » Example Usage

```
data "openstack_identity_role_v3" "admin" {
  name = "admin"
}
```

### » Argument Reference

- name The name of the role.
- domain\_id (Optional) The domain the role belongs to.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.

#### » Attributes Reference

id is set to the ID of the found role. In addition, the following attributes are exported:

- name See Argument Reference above.
- domain\_id See Argument Reference above.
- region See Argument Reference above.

# » openstack\_identity\_user\_v3

Use this data source to get the ID of an OpenStack user.

## » Example Usage

```
data "openstack_identity_user_v3" "user_1" {
  name = "user_1"
}
```

## » Argument Reference

The following arguments are supported:

- default\_project\_id (Optional) The default project this user belongs to.
- domain\_id (Optional) The domain this user belongs to.
- enabled (Optional) Whether the user is enabled or disabled. Valid values are true and false.
- idp\_id (Optional) The identity provider ID of the user.
- name (Optional) The name of the user.
- password\_expires\_at (Optional) Query for expired passwords. See the OpenStack API docs for more information on the query format.
- protocol\_id (Optional) The protocol ID of the user.
- unique\_id (Optional) The unique ID of the user.

#### » Attributes Reference

The following attributes are exported:

- default\_project\_id See Argument Reference above.
- domain\_id See Argument Reference above.
- enabled See Argument Reference above.
- idp\_id See Argument Reference above.
- name See Argument Reference above.
- password\_expires\_at See Argument Reference above.
- protocol\_id See Argument Reference above.
- region The region the user is located in.
- unique\_id See Argument Reference above.
- description A description of the user.

# » openstack\_identity\_service\_v3

Use this data source to get the ID of an OpenStack service.

Note: This usually requires admin privileges.

#### » Example Usage

```
data "openstack_identity_service_v3" "service_1" {
  name = "keystone"
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.
- name (Optional) The service name.
- type (Optional) The service type.
- enabled (Optional) The service status.

### » Attributes Reference

id is set to the ID of the found service. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- type See Argument Reference above.
- enabled See Argument Reference above.
- description The service description.

# > openstack\_images\_image\_v2

Use this data source to get the ID of an available OpenStack image.

## » Example Usage

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Glance client. A Glance client is needed to create an Image that can be used with a compute instance. If omitted, the region argument of the provider is used.
- most\_recent (Optional) If more than one result is returned, use the most recent image.
- name (Optional) The name of the image.
- owner (Optional) The owner (UUID) of the image.
- properties (Optional) a map of key/value pairs to match an image with. All specified properties must be matched.
- size\_min (Optional) The minimum size (in bytes) of the image to return.
- size\_max (Optional) The maximum size (in bytes) of the image to return.
- sort\_direction (Optional) Order the results in either asc or desc.
- sort\_key (Optional) Sort images based on a certain key. Defaults to name.
- tag (Optional) Search for images with a specific tag.
- visibility (Optional) The visibility of the image. Must be one of "public", "private", "community", or "shared". Defaults to "private".
- member\_status (Optional) The status of the image. Must be one of "accepted", "pending", "rejected", or "all".

#### » Attributes Reference

id is set to the ID of the found image. In addition, the following attributes are exported:

- checksum The checksum of the data associated with the image.
- created\_at The date the image was created.
- container format: The format of the image's container.
- disk\_format: The format of the image's disk.
- file the trailing path after the glance endpoint that represent the location of the image or the path to retrieve it.
- metadata The metadata associated with the image. Image metadata allow for meaningfully define the image properties and tags. See https://docs.openstack.org/glance/latest/user/metadefs-concepts.html.
- min\_disk\_gb The minimum amount of disk space required to use the image.
- min\_ram\_mb The minimum amount of ram required to use the image.
- properties Freeform information about the image.
- protected Whether or not the image is protected.
- schema The path to the JSON-schema that represent the image or image
- size\_bytes The size of the image (in bytes).
- tags The tags list of the image.
- updated\_at The date the image was last updated.

# » openstack\_networking\_addressscope\_v2

Use this data source to get the ID of an available OpenStack address-scope.

#### » Example Usage

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve address-scopes. If omitted, the region argument of the provider is used.
- name (Optional) Name of the address-scope.
- ip\_version (Optional) IP version.
- shared (Optional) Indicates whether this address-scope is shared across all projects.

• project\_id - (Optional) The owner of the address-scope.

#### » Attributes Reference

id is set to the ID of the found address-scope. In addition, the following attributes are exported:

- name See Argument Reference above.
- ip\_version See Argument Reference above.
- shared See Argument Reference above.
- project\_id See Argument Reference above.

## » openstack\_networking\_floatingip\_v2

Use this data source to get the ID of an available OpenStack floating IP.

#### » Example Usage

```
data "openstack_networking_floatingip_v2" "floatingip_1" {
  address = "192.168.0.4"
}
```

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve floating IP ids. If omitted, the region argument of the provider is used.
- description (Optional) Human-readable description of the floating IP.
- address (Optional) The IP address of the floating IP.
- pool (Optional) The name of the pool from which the floating IP belongs to.
- port\_id (Optional) The ID of the port the floating IP is attached.
- status status of the floating IP (ACTIVE/DOWN).
- fixed\_ip (Optional) The specific IP address of the internal port which should be associated with the floating IP.
- tags (Optional) The list of floating IP tags to filter.
- tenant\_id (Optional) The owner of the floating IP.

id is set to the ID of the found floating IP. In addition, the following attributes are exported:

- all\_tags A set of string tags applied on the floating IP.
- dns\_name The floating IP DNS name. Available, when Neutron DNS extension is enabled.
- dns\_domain The floating IP DNS domain. Available, when Neutron DNS extension is enabled.

# » openstack\_networking\_network\_v2

Use this data source to get the ID of an available OpenStack network.

#### » Example Usage

```
data "openstack_networking_network_v2" "network" {
  name = "tf_test_network"
}
```

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve networks ids. If omitted, the region argument of the provider is used.
- network id (Optional) The ID of the network.
- name (Optional) The name of the network.
- description (Optional) Human-readable description of the network.
- status (Optional) The status of the network.
- external (Optional) The external routing facility of the network.
- matching\_subnet\_cidr (Optional) The CIDR of a subnet within the network.
- tenant\_id (Optional) The owner of the network.
- availability\_zone\_hints (Optional) The availability zone candidates for the network.
- transparent\_vlan (Optional) The VLAN transparent attribute for the network.

- tags (Optional) The list of network tags to filter.
- mtu (Optional) The network MTU to filter. Available, when Neutron net-mtu extension is enabled.

id is set to the ID of the found network. In addition, the following attributes are exported:

- admin\_state\_up The administrative state of the network.
- name See Argument Reference above.
- description See Argument Reference above.
- region See Argument Reference above.
- external See Argument Reference above.
- shared Specifies whether the network resource can be accessed by any tenant or not.
- availability\_zone\_hints The availability zone candidates for the network.
- transparent\_vlan See Argument Reference above.
- all\_tags The set of string tags applied on the network.
- mtu See Argument Reference above.
- dns\_domain The network DNS domain. Available, when Neutron DNS extension is enabled

# » openstack\_networking\_qos\_bandwidth\_limit\_rule\_v2

Use this data source to get the ID of an available OpenStack QoS bandwidth limit rule.

#### » Example Usage

```
data "openstack_networking_qos_bandwidth_limit_rule_v2" "qos_bandwidth_limit_rule_1" {
   max_kbps = 300
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron QoS bandwidth limit rule. If omitted, the region argument of the provider is used.
- qos\_policy\_id (Required) The QoS policy reference.

- max\_kbps (Optional) The maximum kilobits per second of a QoS bandwidth limit rule.
- max\_burst\_kbps (Optional) The maximum burst size in kilobits of a QoS bandwidth limit rule.
- direction (Optional) The direction of traffic.

id is set to the qos\_policy\_id/bandwidth\_limit\_rule\_id format of the found QoS bandwidth limit rule. In addition, the following attributes are exported:

- region See Argument Reference above.
- qos\_policy\_id See Argument Reference above.
- max\_kbps See Argument Reference above.
- max\_burst\_kbps See Argument Reference above.
- direction See Argument Reference above.

## » openstack\_networking\_qos\_dscp\_marking\_rule\_v2

Use this data source to get the ID of an available OpenStack QoS DSCP marking rule.

### » Example Usage

```
data "openstack_networking_qos_dscp_marking_rule_v2" "qos_dscp_marking_rule_1" {
   dscp_mark = 26
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron QoS DSCP marking rule. If omitted, the region argument of the provider is used.
- qos\_policy\_id (Required) The QoS policy reference.
- dscp\_mark (Optional) The value of a DSCP mark.

id is set to the qos\_policy\_id/dscp\_marking\_rule\_id format of the found QoS DSCP marking rule. In addition, the following attributes are exported:

- region See Argument Reference above.
- qos\_policy\_id See Argument Reference above.
- dscp\_mark See Argument Reference above.

## » openstack\_networking\_qos\_minimum\_bandwidth\_rule\_v2

Use this data source to get the ID of an available OpenStack QoS minimum bandwidth rule.

#### » Example Usage

```
data "openstack_networking_qos_minimum_bandwidth_rule_v2" "qos_min_bw_rule_1" {
   min_kbps = 2000
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron QoS minimum bandwidth rule. If omitted, the region argument of the provider is used.
- qos\_policy\_id (Required) The QoS policy reference.
- min\_kbps (Optional) The value of a minimum kbps bandwidth.

#### » Attributes Reference

id is set to the qos\_policy\_id/minimum\_bandwidth\_rule\_id format of the found QoS minimum bandwidth rule. In addition, the following attributes are exported:

- region See Argument Reference above.
- qos policy id See Argument Reference above.
- min kbps See Argument Reference above.

## » openstack\_networking\_qos\_policy\_v2

Use this data source to get the ID of an available OpenStack QoS policy.

#### » Example Usage

```
data "openstack_networking_qos_policy_v2" "qos_policy_1" {
  name = "qos_policy_1"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to retrieve a QoS policy ID. If omitted, the region argument of the provider is used.
- name (Optional) The name of the QoS policy.
- project\_id (Optional) The owner of the QoS policy.
- shared (Optional) Whether this QoS policy is shared across all projects.
- description (Optional) The human-readable description for the QoS policy.
- is\_default (Optional) Whether the QoS policy is default policy or not.
- tags (Optional) The list of QoS policy tags to filter.

#### » Attributes Reference

id is set to the ID of the found QoS policy. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- created\_at The time at which QoS policy was created.
- updated\_at The time at which QoS policy was created.
- shared See Argument Reference above.
- description See Argument Reference above.
- is\_default See Argument Reference above.
- revision\_number The revision number of the QoS policy.
- all\_tags The set of string tags applied on the QoS policy.

## » openstack\_networking\_router\_v2

Use this data source to get the ID of an available OpenStack router.

#### » Example Usage

```
data "openstack_networking_router_v2" "router" {
  name = "router_1"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve router ids. If omitted, the region argument of the provider is used.
- router\_id (Optional) The UUID of the router resource.
- name (Optional) The name of the router.
- description (Optional) Human-readable description of the router.
- admin\_state\_up (Optional) Administrative up/down status for the router (must be "true" or "false" if provided).
- distributed (Optional) Indicates whether or not to get a distributed router.
- status (Optional) The status of the router (ACTIVE/DOWN).
- tags (Optional) The list of router tags to filter.
- tenant\_id (Optional) The owner of the router.

## » Attributes Reference

id is set to the ID of the found router. In addition, the following attributes are exported:

- enable\_snat The value that points out if the Source NAT is enabled on the router.
- external\_network\_id The network UUID of an external gateway for the router.
- availability\_zone\_hints The availability zone that is used to make router resources highly available.
- external\_fixed\_ip The external fixed IPs of the router.

The external\_fixed\_ip block supports:

- subnet\_id- Subnet in which the fixed IP belongs to.
- ip\_address The IP address to set on the router.
- all\_tags The set of string tags applied on the router.

# » openstack\_networking\_secgroup\_v2

Use this data source to get the ID of an available OpenStack security group.

## » Example Usage

```
data "openstack_networking_secgroup_v2" "secgroup" {
  name = "tf_test_secgroup"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client.
   A Neutron client is needed to retrieve security groups ids. If omitted, the region argument of the provider is used.
- secgroup\_id (Optional) The ID of the security group.
- name (Optional) The name of the security group.
- description (Optional) Human-readable description the the subnet.
- tags (Optional) The list of security group tags to filter.
- tenant\_id (Optional) The owner of the security group.

#### » Attributes Reference

id is set to the ID of the found security group. In addition, the following attributes are exported:

- name See Argument Reference above.
- description- See Argument Reference above.
- all\_tags The set of string tags applied on the security group.
- region See Argument Reference above.

## » openstack\_networking\_subnet\_v2

Use this data source to get the ID of an available OpenStack subnet.

#### » Example Usage

```
data "openstack_networking_subnet_v2" "subnet_1" {
  name = "subnet_1"
}
```

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve subnet ids. If omitted, the region argument of the provider is used.
- name (Optional) The name of the subnet.
- description (Optional) Human-readable description for the subnet.
- dhcp\_enabled (Optional) If the subnet has DHCP enabled.
- dhcp\_disabled (Optional) If the subnet has DHCP disabled.
- ip\_version (Optional) The IP version of the subnet (either 4 or 6).
- ipv6\_address\_mode (Optional) The IPv6 address mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- ipv6\_ra\_mode (Optional) The IPv6 Router Advertisement mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- gateway\_ip (Optional) The IP of the subnet's gateway.
- cidr (Optional) The CIDR of the subnet.
- subnet\_id (Optional) The ID of the subnet.
- subnetpool\_id (Optional) The ID of the subnetpool associated with the subnet.
- network\_id (Optional) The ID of the network the subnet belongs to.
- tenant\_id (Optional) The owner of the subnet.
- tags (Optional) The list of subnet tags to filter.

id is set to the ID of the found subnet. In addition, the following attributes are exported:

- allocation\_pools Allocation pools of the subnet.
- enable\_dhcp Whether the subnet has DHCP enabled or not.
- dns\_nameservers DNS Nameservers of the subnet.
- host routes Host Routes of the subnet.
- region See Argument Reference above.
- all\_tags A set of string tags applied on the subnet.

# » openstack\_networking\_subnetpool\_v2

Use this data source to get the ID of an available OpenStack subnetpool.

## » Example Usage

```
data "openstack_networking_subnetpool_v2" "subnetpool_1" {
  name = "subnetpool_1"
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to retrieve a subnetpool id. If omitted, the region argument of the provider is used.
- name (Optional) The name of the subnetpool.
- default\_quota (Optional) The per-project quota on the prefix space that can be allocated from the subnetpool for project subnets.
- project\_id (Optional) The owner of the subnetpool.
- prefixes (Optional) A list of subnet prefixes that are assigned to the subnetpool.
- default\_prefixlen (Optional) The size of the subnetpool default prefix length.
- min\_prefixlen (Optional) The size of the subnetpool min prefix length.
- max\_prefixlen (Optional) The size of the subnetpool max prefix length.
- address\_scope\_id (Optional) The Neutron address scope that subnet-pools is assigned to.

- ip\_version The IP protocol version.
- shared (Optional) Whether this subnetpool is shared across all projects.
- description (Optional) The human-readable description for the subnetpool.
- is\_default (Optional) Whether the subnetpool is default subnetpool or not.
- tags (Optional) The list of subnetpool tags to filter.

id is set to the ID of the found subnetpool. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- default\_quota See Argument Reference above.
- project\_id See Argument Reference above.
- created\_at The time at which subnetpool was created.
- updated\_at The time at which subnetpool was created.
- prefixes See Argument Reference above.
- default\_prefixlen See Argument Reference above.
- min\_prefixlen See Argument Reference above.
- max\_prefixlen See Argument Reference above.
- address\_scope\_id See Argument Reference above.
- ip\_version -The IP protocol version.
- shared See Argument Reference above.
- description See Argument Reference above.
- is\_default See Argument Reference above.
- revision\_number The revision number of the subnetpool.
- all\_tags The set of string tags applied on the subnetpool.

# $ightsymbol{"}$ openstack\_networking\_port\_v2

Use this data source to get the ID of an available OpenStack port.

```
data "openstack_networking_port_v2" "port_1" {
  name = "port_1"
}
```

- region (Optional) The region in which to obtain the V2 Neutron client.
   A Neutron client is needed to retrieve port ids. If omitted, the region argument of the provider is used.
- project\_id (Optional) The owner of the port.
- port\_id (Optional) The ID of the port.
- name (Optional) The name of the port.
- description (Optional) Human-readable description of the port.
- admin\_state\_up (Optional) The administrative state of the port.
- network\_id (Optional) The ID of the network the port belongs to.
- device\_owner (Optional) The device owner of the port.
- mac\_address (Optional) The MAC address of the port.
- device\_id (Optional) The ID of the device the port belongs to.
- fixed\_ip (Optional) The port IP address filter.
- status (Optional) The status of the port.
- security\_group\_ids (Optional) The list of port security group IDs to filter.
- tags (Optional) The list of port tags to filter.
- dns\_name (Optional) The port DNS name to filter. Available, when Neutron DNS extension is enabled.

#### » Attributes Reference

id is set to the ID of the found port. In addition, the following attributes are exported:

- region See Argument Reference above.
- project\_id See Argument Reference above.
- port\_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- network\_id See Argument Reference above.
- device\_owner See Argument Reference above.

- mac\_address See Argument Reference above.
- device\_id See Argument Reference above.
- allowed\_address\_pairs An IP/MAC Address pair of additional IP addresses that can be active on this port. The structure is described below.
- all\_fixed\_ips The collection of Fixed IP addresses on the port in the order returned by the Network v2 API.
- all\_security\_group\_ids The set of security group IDs applied on the port.
- all\_tags The set of string tags applied on the port.
- extra\_dhcp\_option An extra DHCP option configured on the port. The structure is described below.
- binding The port binding information. The structure is described below.
- dns\_name See Argument Reference above.
- dns\_assignment The list of maps representing port DNS assignments.

The allowed\_address\_pairs attribute has fields below:

- ip\_address The additional IP address.
- mac\_address The additional MAC address.

The extra\_dhcp\_option attribute has fields below:

- name Name of the DHCP option.
- value Value of the DHCP option.
- ip\_version IP protocol version

The binding attribute has fields below:

- host\_id The ID of the host, which has the allocatee port.
- profile A JSON string containing the binding profile information.
- vnic\_type VNIC type for the port.
- vif\_details A map of JSON strings containing additional details for this specific binding.
- vif\_type The VNIC type of the port binding.

# ${\tt "openstack\_networking\_port\_ids\_v2}$

Use this data source to get a list of Openstack Port IDs matching the specified criteria.

## » Example Usage

```
data "openstack_networking_port_ids_v2" "ports" {
  name = "port"
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve port ids. If omitted, the region argument of the provider is used.
- project\_id (Optional) The owner of the port.
- name (Optional) The name of the port.
- description (Optional) Human-readable description of the port.
- admin\_state\_up (Optional) The administrative state of the port.
- network\_id (Optional) The ID of the network the port belongs to.
- device\_owner (Optional) The device owner of the port.
- mac\_address (Optional) The MAC address of the port.
- device\_id (Optional) The ID of the device the port belongs to.
- fixed\_ip (Optional) The port IP address filter.
- status (Optional) The status of the port.
- security\_group\_ids (Optional) The list of port security group IDs to filter.
- tags (Optional) The list of port tags to filter.
- sort\_key (Optional) Sort ports based on a certain key. Defaults to none.
- sort\_direction (Optional) Order the results in either asc or desc. Defaults to none.

#### » Attributes Reference

ids is set to the list of Openstack Port IDs.

# » openstack\_networking\_trunk\_v2

Use this data source to get the ID of an available OpenStack trunk.

## » Example Usage

```
data "openstack_networking_trunk_v2" "trunk_1" {
  name = "trunk_1"
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve trunk ids. If omitted, the region argument of the provider is used.
- project\_id (Optional) The owner of the trunk.
- trunk\_id (Optional) The ID of the trunk.
- name (Optional) The name of the trunk.
- description (Optional) Human-readable description of the trunk.
- port\_id (Optional) The ID of the trunk parent port.
- admin\_state\_up (Optional) The administrative state of the trunk.
- status (Optional) The status of the trunk.
- tags (Optional) The list of trunk tags to filter.

#### » Attributes Reference

id is set to the ID of the found trunk. In addition, the following attributes are exported:

- all\_tags The set of string tags applied on the trunk.
- sub\_port The set of the trunk subports. The structure of each subport is described below.

The sub\_port attribute has fields below:

- port\_id The ID of the trunk subport.
- segmentation\_type The segmenation tecnology used, e.g., "vlan".
- segmentation\_id The numeric id of the subport segment.

## » openstack sharedfilesystem availability zones v2

Use this data source to get a list of Shared File System availability zones from OpenStack

#### » Example Usage

data "openstack\_sharedfilesystem\_availability\_zones\_v2" "zones" {}

### » Argument Reference

• region - (Optional) The region in which to obtain the V2 Shared File System client. If omitted, the region argument of the provider is used.

#### » Attributes Reference

id is set to hash of the returned zone list. In addition, the following attributes are exported:

- region See Argument Reference above.
- names The names of the availability zones, ordered alphanumerically.

# ${\tt » openstack\_sharedfilesystem\_share\_v2}$

Use this data source to get the ID of an available Shared File System share.

## » Example Usage

```
data "openstack_sharedfilesystem_share_v2" "share_1" {
  name = "share_1"
}
```

- name (Optional) The name of the share.
- description (Optional) The human-readable description for the share.
- project\_id (Optional) The owner of the share.
- snapshot\_id (Optional) The UUID of the share's base snapshot.

- share\_network\_id (Optional) The UUID of the share's share network.
- export\_location\_path (Optional) The export location path of the share. Available since Manila API version 2.35.
- metadata (Optional) One or more metadata key and value pairs as a dictionary of strings.
- status (Optional) A share status filter. A valid value is creating, error, available, deleting, error\_deleting, manage\_starting, manage\_error, unmanage\_starting, unmanage\_error, unmanaged, extending, extending\_error, shrinking, shrinking\_error, or shrinking\_possible\_data\_loss\_error.
- is\_public (Optional) The level of visibility for the share. length.

### » Attributes Reference

id is set to the ID of the found share. In addition, the following attributes are exported:

- name See Argument Reference above.
- description See Argument Reference above.
- project\_id See Argument Reference above.
- snapshot\_id See Argument Reference above.
- share\_network\_id See Argument Reference above.
- export\_location\_path See Argument Reference above.
- metadata See Argument Reference above.
- status See Argument Reference above.
- is public See Argument Reference above.
- region The region in which to obtain the V2 Shared File System client.
- availability zone The share availability zone.
- share\_proto The share protocol.
- size The share size, in GBs.
- export\_locations A list of export locations. For example, when a share server has more than one network interface, it can have multiple export locations.

# ${\tt "openstack\_shared filesystem\_share network\_v2}$

Use this data source to get the ID of an available Shared File System share network.

## » Example Usage

```
data "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
  name = "sharenetwork_1"
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to read a share network. If omitted, the region argument of the provider is used.
- name (Optional) The name of the share network.
- description (Optional) The human-readable description of the share network.
- project\_id (Optional) The owner of the share network.
- neutron\_net\_id (Optional) The neutron network UUID of the share network.
- neutron\_subnet\_id (Optional) The neutron subnet UUID of the share network.
- security\_service\_id (Optional) The security service IDs associated with the share network.
- network\_type (Optional) The share network type. Can either be VLAN, VXLAN, GRE, or flat.
- segmentation\_id (Optional) The share network segmentation ID.
- cidr (Optional) The share network CIDR.
- ip\_version (Optional) The IP version of the share network. Can either be 4 or 6.

#### » Attributes Reference

 ${\tt id}$  is set to the ID of the found share network . In addition, the following attributes are exported:

- region See Argument Reference above.
- project\_id The owner of the Share Network.
- name See Argument Reference above.
- description See Argument Reference above.
- neutron\_net\_id See Argument Reference above.
- neutron\_subnet\_id See Argument Reference above.

- security\_service\_id See Argument Reference above.
- network\_type See Argument Reference above.
- segmentation\_id See Argument Reference above.
- cidr See Argument Reference above.
- ip\_version See Argument Reference above.
- security\_service\_ids The list of security service IDs associated with the share network.

# » openstack\_sharedfilesystem\_snapshot\_v2

Use this data source to get the ID of an available Shared File System snapshot.

## » Example Usage

```
data "openstack_sharedfilesystem_snapshot_v2" "snapshot_1" {
  name = "snapshot_1"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Shared File System client.
- name (Optional) The name of the snapshot.
- description (Optional) The human-readable description of the snapshot.
- project\_id (Optional) The owner of the snapshot.
- status (Optional) A snapshot status filter. A valid value is available, error, creating, deleting, manage\_starting, manage\_error, unmanage starting, unmanage error or error deleting.

### » Attributes Reference

id is set to the ID of the found snapshot. In addition, the following attributes are exported:

- name See Argument Reference above.
- description See Argument Reference above.
- project\_id See Argument Reference above.
- status See Argument Reference above.
- size The snapshot size, in GBs.

- share\_id The UUID of the source share that was used to create the snapshot.
- share\_proto The file system protocol of a share snapshot.
- share\_size The share snapshot size, in GBs.

# » openstack\_keymanager\_secret\_v1

Use this data source to get the ID and the payload of an available Barbican secret

Important Security Notice The payload of this data source will be stored *unencrypted* in your Terraform state file. Use of this resource for production deployments is *not* recommended.

## » Example Usage

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 KeyManager client. A KeyManager client is needed to fetch a secret. If omitted, the region argument of the provider is used.
- name (Optional) The Secret name.
- bit length (Optional) The Secret bit length.
- algorithm (Optional) The Secret algorithm.
- mode (Optional) The Secret mode.
- secret\_type (Optional) The Secret type. For more information see Secret types.
- acl\_only (Optional) Select the Secret with an ACL that contains the user. Project scope is ignored. Defaults to false.
- expiration\_filter (Optional) Date filter to select the Secret with expiration matching the specified criteria. See Date Filters below for more detail.

- created\_at\_filter (Optional) Date filter to select the Secret with created matching the specified criteria. See Date Filters below for more detail.
- updated\_at\_filter (Optional) Date filter to select the Secret with updated matching the specified criteria. See Date Filters below for more detail.

### » Date Filters

The values for the expiration\_filter, created\_at\_filter, and updated\_at\_filter parameters are comma-separated lists of time stamps in RFC3339 format. The time stamps can be prefixed with any of these comparison operators: gt: (greater-than), gte: (greater-than-or-equal), lt: (less-than), lte: (less-than-or-equal).

For example, to get a passphrase a Secret with CBC moda, that will expire in January of 2020:

### » Attributes Reference

The following attributes are exported:

- secret\_ref The secret reference / where to find the secret.
- region See Argument Reference above.
- name See Argument Reference above.
- bit\_length See Argument Reference above.
- algorithm See Argument Reference above.
- mode See Argument Reference above.
- secret\_type See Argument Reference above.
- acl\_only See Argument Reference above.
- expiration\_filter See Argument Reference above.
- created\_at\_filter See Argument Reference above.
- updated\_at\_filter See Argument Reference above.
- payload The secret payload.
- payload\_content\_type The Secret content type.
- payload\_content\_encoding The Secret encoding.
- content\_types The map of the content types, assigned on the secret.
- creator\_id The creator of the secret.
- status The status of the secret.

- expiration The date the secret will expire.
- created\_at The date the secret was created.
- updated at The date the secret was last updated.
- metadata The map of metadata, assigned on the secret, which has been explicitly and implicitly added.
- acl The list of ACLs assigned to a secret. The read structure is described below.

The acl read attribute supports:

- project\_access Whether the secret is accessible project wide.
- users The list of user IDs, which are allowed to access the secret, when project\_access is set to false.
- created at The date the secret ACL was created.
- updated\_at The date the secret ACL was last updated.

# » openstack\_keymanager\_container\_v1

Use this data source to get the ID of an available Barbican container.

# » Example Usage

```
data "openstack_keymanager_container_v1" "example" {
  name = "my_container"
}
```

# » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 KeyManager client. A KeyManager client is needed to fetch a container. If omitted, the region argument of the provider is used.
- name (Optional) The Container name.

### » Attributes Reference

The following attributes are exported:

- container\_ref The container reference / where to find the container.
- region See Argument Reference above.

- name See Argument Reference above.
- type The container type.
- secret\_refs A set of dictionaries containing references to secrets. The structure is described below.
- creator\_id The creator of the container.
- status The status of the container.
- created\_at The date the container was created.
- updated\_at The date the container was last updated.
- consumers The list of the container consumers. The structure is described below.
- acl The list of ACLs assigned to a container. The read structure is described below.

The secret\_refs block supports:

- name The name of the secret reference. The reference names must correspond the container type, more details are available here.
- secret\_ref The secret reference / where to find the secret, URL.

The consumers block supports:

- name The name of the consumer.
- url The consumer URL.

The acl read attribute supports:

- project\_access Whether the container is accessible project wide.
- users The list of user IDs, which are allowed to access the container, when project\_access is set to false.
- created\_at The date the container ACL was created.
- updated\_at The date the container ACL was last updated.

# » openstack\_blockstorage\_volume\_v1

Manages a V1 volume resource within OpenStack.

### » Example Usage

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes). Changing this creates a new volume.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- availability\_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- image\_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- snapshot\_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source\_vol\_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- volume\_type (Optional) The type of volume to create. Changing this
  creates a new volume.

## » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- availability\_zone See Argument Reference above.
- image\_id See Argument Reference above.
- source\_vol\_id See Argument Reference above.
- snapshot\_id See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type See Argument Reference above.

• attachment - If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.

### » Import

Volumes can be imported using the id, e.g.

\$ terraform import openstack\_blockstorage\_volume\_v1.volume\_1 ea257959-eeb1-4c10-8d33-26f0409

# 

Manages a V2 block storage quotaset resource within OpenStack.

Note: This usually requires admin privileges.

**Note:** This resource has a no-op deletion so no actual actions will be done against the OpenStack API in case of delete call.

## » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = project_1
}

resource "openstack_blockstorage_quotaset_v2" "quotaset_1" {
   project_id = "${openstack_identity_project_v3.project_1.id}"
   volumes = 10
   snapshots = 4
   gigabytes = 100
   per_volume_gigabytes = 10
   backups = 4
   backup_gigabytes = 10
   groups = 100
}
```

## » Argument Reference

The following arguments are supported:

• region - (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new quotaset.

- project\_id (Required) ID of the project to manage quotas. Changing this creates a new quotaset.
- volumes (Optional) Quota value for volumes. Changing this updates the existing quotaset.
- snapshots (Optional) Quota value for snapshots. Changing this updates the existing quotaset.
- gigabytes (Optional) Quota value for gigabytes. Changing this updates the existing quotaset.
- per\_volume\_gigabytes (Optional) Quota value for gigabytes per volume . Changing this updates the existing quotaset.
- backups (Optional) Quota value for backups. Changing this updates the existing quotaset.
- backup\_gigabytes (Optional) Quota value for backup gigabytes. Changing this updates the existing quotaset.
- groups (Optional) Quota value for groups. Changing this updates the existing quotaset.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
  - project\_id See Argument Reference above.
  - volumes See Argument Reference above.
  - snapshots See Argument Reference above.
  - gigabytes See Argument Reference above.
  - per\_volume\_gigabytes See Argument Reference above.
  - backups See Argument Reference above.
  - backup\_gigabytes See Argument Reference above.
  - groups See Argument Reference above.

### » Import

Quotasets can be imported using the project\_id, e.g.

\$ terraform import openstack\_blockstorage\_quotaset\_v2.quotaset\_1 2a0f2240-c5e6-41de-896d-e8

# » openstack\_blockstorage\_volume\_v2

Manages a V2 volume resource within OpenStack.

## » Example Usage

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes). Changing this creates a new volume.
- availability\_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- consistency\_group\_id (Optional) The consistency group to place the volume in.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- image\_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- snapshot\_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source\_replica (Optional) The volume ID to replicate with.
- source\_vol\_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- volume\_type (Optional) The type of volume to create. Changing this creates a new volume.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- availability\_zone See Argument Reference above.
- image\_id See Argument Reference above.
- source\_vol\_id See Argument Reference above.
- snapshot\_id See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.

## » Import

Volumes can be imported using the id, e.g.

# » openstack blockstorage volume attach v2

This resource is experimental and may be removed in the future! Feedback is requested if you find this resource useful or if you find any problems with it.

Creates a general purpose attachment connection to a Block Storage volume using the OpenStack Block Storage (Cinder) v2 API. Depending on your Block Storage service configuration, this resource can assist in attaching a volume to a non-OpenStack resource such as a bare-metal server or a remote virtual machine in a different cloud provider.

This does not actually attach a volume to an instance. Please use the openstack\_compute\_volume\_attach\_v2 resource for that.

### » Example Usage

```
resource "openstack_blockstorage_volume_v2" "volume_1" {
  name = "volume_1"
  size = 1
}
```

```
resource "openstack_blockstorage_volume_attach_v2" "va_1" {
  volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
  device = "auto"
  host_name = "devstack"
  ip_address = "192.168.255.10"
  initiator = "iqn.1993-08.org.debian:01:e9861fb1859"
  os_type = "linux2"
  platform = "x86_64"
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Block Storage client. A Block Storage client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- attach\_mode (Optional) Specify whether to attach the volume as Read-Only (ro) or Read-Write (rw). Only values of ro and rw are accepted. If left unspecified, the Block Storage API will apply a default of rw.
- device (Optional) The device to tell the Block Storage service this volume will be attached as. This is purely for informational purposes. You can specify auto or a device such as /dev/vdc.
- host name (Required) The host to attach the volume to.
- initiator (Optional) The iSCSI initiator string to make the connection.
- ip\_address (Optional) The IP address of the host\_name above.
- multipath (Optional) Whether to connect to this volume via multipath.
- os\_type (Optional) The iSCSI initiator OS type.
- platform (Optional) The iSCSI initiator platform.
- volume\_id (Required) The ID of the Volume to attach to an Instance.
- wwpn (Optional) An array of wwpn strings. Used for Fibre Channel connections.
- wwnn (Optional) A wwnn name. Used for Fibre Channel connections.

#### » Attributes Reference

In addition to the above, the following attributes are exported:

- data This is a map of key/value pairs that contain the connection information. You will want to pass this information to a provisioner script to finalize the connection. See below for more information.
- driver\_volume\_type The storage driver that the volume is based on.
- mount\_point\_base A mount point base name for shared storage.

### » Volume Connection Data

Upon creation of this resource, a data exported attribute will be available. This attribute is a set of key/value pairs that contains the information required to complete the block storage connection.

As an example, creating an iSCSI-based volume will return the following:

```
data.access_mode = rw
data.auth_method = CHAP
data.auth_password = xUhbGKQ8QCwKmHQ2
data.auth_username = Sphn5X4EoyFUUMYVYSA4
data.target_iqn = iqn.2010-10.org.openstack:volume-2d87ed25-c312-4f42-be1d-3b36b014561d
data.target_portal = 192.168.255.10:3260
data.volume_id = 2d87ed25-c312-4f42-be1d-3b36b014561d
```

This information can then be fed into a provisioner or a template shell script, where the final result would look something like:

```
iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --interface defaultiscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --login iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node -T ${self.data.target_iqn} --op update
```

The contents of data will vary from each Block Storage service. You must have a good understanding of how the service is configured and how to make the appropriate final connection. However, if used correctly, this has the flexibility to be able to attach OpenStack Block Storage volumes to non-OpenStack resources.

### » Import

It is not possible to import this resource.

# » openstack\_blockstorage\_quotaset\_v3

Manages a V3 block storage quotaset resource within OpenStack.

Note: This usually requires admin privileges.

**Note:** This resource has a no-op deletion so no actual actions will be done against the OpenStack API in case of delete call.

## » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = project_1
}

resource "openstack_blockstorage_quotaset_v3" "quotaset_1" {
   project_id = "${openstack_identity_project_v3.project_1.id}"
   volumes = 10
   snapshots = 4
   gigabytes = 100
   per_volume_gigabytes = 10
   backups = 4
   backup_gigabytes = 10
   groups = 100
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new quotaset.
- project\_id (Required) ID of the project to manage quotas. Changing this creates a new quotaset.
- volumes (Optional) Quota value for volumes. Changing this updates the existing quotaset.
- snapshots (Optional) Quota value for snapshots. Changing this updates the existing quotaset.
- gigabytes (Optional) Quota value for gigabytes. Changing this updates the existing quotaset.
- per\_volume\_gigabytes (Optional) Quota value for gigabytes per volume . Changing this updates the existing quotaset.

- backups (Optional) Quota value for backups. Changing this updates the existing quotaset.
- backup\_gigabytes (Optional) Quota value for backup gigabytes. Changing this updates the existing quotaset.
- groups (Optional) Quota value for groups. Changing this updates the existing quotaset.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- project\_id See Argument Reference above.
- volumes See Argument Reference above.
- snapshots See Argument Reference above.
- gigabytes See Argument Reference above.
- per\_volume\_gigabytes See Argument Reference above.
- backups See Argument Reference above.
- backup\_gigabytes See Argument Reference above.
- groups See Argument Reference above.

### » Import

Quotasets can be imported using the project\_id, e.g.

\$ terraform import openstack\_blockstorage\_quotaset\_v3.quotaset\_1 2a0f2240-c5e6-41de-896d-e86

# » openstack\_blockstorage\_volume\_v3

Manages a V3 volume resource within OpenStack.

### » Example Usage

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes).
- enable\_online\_resize (Optional) When this option is set it allows extending attached volumes. Note: updating size of an attached volume requires Cinder support for version 3.42 and a compatible storage driver.
- availability\_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- consistency\_group\_id (Optional) The consistency group to place the volume in.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- image\_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- snapshot\_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source\_replica (Optional) The volume ID to replicate with.
- source\_vol\_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- volume\_type (Optional) The type of volume to create. Changing this
  creates a new volume.
- multiattach (Optional) Allow the volume to be attached to more than one Compute instance.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.

- name See Argument Reference above.
- description See Argument Reference above.
- availability\_zone See Argument Reference above.
- image\_id See Argument Reference above.
- source\_vol\_id See Argument Reference above.
- snapshot\_id See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.
- multiattach See Argument Reference above.

## » Import

Volumes can be imported using the id, e.g.

\$ terraform import openstack\_blockstorage\_volume\_v3.volume\_1 ea257959-eeb1-4c10-8d33-26f0409

# » openstack\_blockstorage\_volume\_attach\_v3

This resource is experimental and may be removed in the future! Feedback is requested if you find this resource useful or if you find any problems with it.

Creates a general purpose attachment connection to a Block Storage volume using the OpenStack Block Storage (Cinder) v3 API. Depending on your Block Storage service configuration, this resource can assist in attaching a volume to a non-OpenStack resource such as a bare-metal server or a remote virtual machine in a different cloud provider.

This does not actually attach a volume to an instance. Please use the openstack\_compute\_volume\_attach\_v2 resource for that.

### » Example Usage

```
resource "openstack_blockstorage_volume_v3" "volume_1" {
   name = "volume_1"
   size = 1
}

resource "openstack_blockstorage_volume_attach_v3" "va_1" {
   volume_id = "${openstack_blockstorage_volume_v3.volume_1.id}"
   device = "auto"
   host name = "devstack"
```

```
ip_address = "192.168.255.10"
initiator = "iqn.1993-08.org.debian:01:e9861fb1859"
os_type = "linux2"
platform = "x86_64"
}
```

# » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V3 Block Storage client. A Block Storage client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- attach\_mode (Optional) Specify whether to attach the volume as Read-Only (ro) or Read-Write (rw). Only values of ro and rw are accepted. If left unspecified, the Block Storage API will apply a default of rw.
- device (Optional) The device to tell the Block Storage service this volume will be attached as. This is purely for informational purposes. You can specify auto or a device such as /dev/vdc.
- host\_name (Required) The host to attach the volume to.
- initiator (Optional) The iSCSI initiator string to make the connection.
- ip\_address (Optional) The IP address of the host\_name above.
- multipath (Optional) Whether to connect to this volume via multipath.
- os type (Optional) The iSCSI initiator OS type.
- platform (Optional) The iSCSI initiator platform.
- volume\_id (Required) The ID of the Volume to attach to an Instance.
- wwpn (Optional) An array of wwpn strings. Used for Fibre Channel connections.
- wwnn (Optional) A wwnn name. Used for Fibre Channel connections.

#### » Attributes Reference

In addition to the above, the following attributes are exported:

- data This is a map of key/value pairs that contain the connection information. You will want to pass this information to a provisioner script to finalize the connection. See below for more information.
- driver\_volume\_type The storage driver that the volume is based on.

• mount\_point\_base - A mount point base name for shared storage.

### » Volume Connection Data

Upon creation of this resource, a data exported attribute will be available. This attribute is a set of key/value pairs that contains the information required to complete the block storage connection.

As an example, creating an iSCSI-based volume will return the following:

```
data.access_mode = rw
data.auth_method = CHAP
data.auth_password = xUhbGKQ8QCwKmHQ2
data.auth_username = Sphn5X4EoyFUUMYVYSA4
data.target_iqn = iqn.2010-10.org.openstack:volume-2d87ed25-c312-4f42-be1d-3b36b014561d
data.target_portal = 192.168.255.10:3260
data.volume_id = 2d87ed25-c312-4f42-be1d-3b36b014561d
```

This information can then be fed into a provisioner or a template shell script, where the final result would look something like:

```
iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --interface default iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --login iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --rescan
```

The contents of data will vary from each Block Storage service. You must have a good understanding of how the service is configured and how to make the appropriate final connection. However, if used correctly, this has the flexibility to be able to attach OpenStack Block Storage volumes to non-OpenStack resources.

## » Import

It is not possible to import this resource.

# $ightsymbol{"} m openstack\_compute\_flavor\_v2$

Manages a V2 flavor resource within OpenStack.

## » Example Usage

```
resource "openstack_compute_flavor_v2" "test-flavor" {
  name = "my-flavor"
  ram = "8096"
  vcpus = "2"
  disk = "20"

extra_specs = {
    "hw:cpu_policy" = "CPU-POLICY",
    "hw:cpu_thread_policy" = "CPU-THREAD-POLICY"
  }
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Flavors are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new flavor.
- name (Required) A unique name for the flavor. Changing this creates a new flavor.
- ram (Required) The amount of RAM to use, in megabytes. Changing this creates a new flavor.
- vcpus (Required) The number of virtual CPUs to use. Changing this creates a new flavor.
- disk (Required) The amount of disk space in gigabytes to use for the root (/) partition. Changing this creates a new flavor.
- swap (Optional) The amount of disk space in megabytes to use. If unspecified, the default is 0. Changing this creates a new flavor.
- rx\_tx\_factor (Optional) RX/TX bandwith factor. The default is 1. Changing this creates a new flavor.
- is\_public (Optional) Whether the flavor is public. Changing this creates a new flavor.
- extra\_specs (Optional) Key/Value pairs of metadata for the flavor.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- ram See Argument Reference above.
- vcpus See Argument Reference above.
- disk See Argument Reference above.
- swap See Argument Reference above.
- rx\_tx\_factor See Argument Reference above.
- is\_public See Argument Reference above.
- extra\_specs See Argument Reference above.

### » Import

Flavors can be imported using the ID, e.g.

\$ terraform import openstack\_compute\_flavor\_v2.my-flavor 4142e64b-1b35-44a0-9b1e-5affc7af110

# » openstack\_compute\_flavor\_access\_v2

Manages a project access for flavor V2 resource within OpenStack.

Note: You *must* have admin privileges in your OpenStack cloud to use this resource.

## » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = "my-project"
}

resource "openstack_compute_flavor_v2" "flavor_1" {
   name = "my-flavor"
   ram = "8096"
   vcpus = "2"
   disk = "20"
   is_public = false
}

resource "openstack_compute_flavor_access_v2" "access_1" {
```

```
tenant_id = "${openstack_identity_project_v3.project_1.id}"
flavor_id = "${openstack_compute_flavor_v2.flavor_1.id}"
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used. Changing this creates a new flavor access.
- flavor\_id (Required) The UUID of flavor to use. Changing this creates a new flavor access.
- tenant\_id (Required) The UUID of tenant which is allowed to use the flavor. Changing this creates a new flavor access.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- flavor id See Argument Reference above.
- tenant\_id See Argument Reference above.

### » Import

This resource can be imported by specifying all two arguments, separated by a forward slash:

\$ terraform import openstack\_compute\_flavor\_access\_v2.access\_1 <flavor\_id>/<tenant\_id>

# » openstack\_compute\_floatingip\_v2

Manages a V2 floating IP resource within OpenStack Nova (compute) that can be used for compute instances.

Please note that managing floating IPs through the OpenStack Compute API has been deprecated. Unless you are using an older OpenStack environment, it is recommended to use the openstack\_networking\_floatingip\_v2 resource instead, which uses the OpenStack Networking API.

## » Example Usage

```
resource "openstack_compute_floatingip_v2" "floatip_1" {
  pool = "public"
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a floating IP that can be used with a compute instance. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- pool (Required) The name of the pool from which to obtain the floating IP. Changing this creates a new floating IP.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- pool See Argument Reference above.
- address The actual floating IP address itself.
- fixed\_ip The fixed IP address corresponding to the floating IP.
- instance\_id UUID of the compute instance associated with the floating IP.

## » Import

Floating IPs can be imported using the id, e.g.

\$ terraform import openstack\_compute\_floatingip\_v2.floatip\_1 89c60255-9bd6-460c-822a-e2b959e

# $ightsymbol{"} ightsymbol{"} openstack\_compute\_floatingip\_associate\_v2$

Associate a floating IP to an instance. This can be used instead of the floating\_ip options in openstack\_compute\_instance\_v2.

## » Example Usage

» Automatically detect the correct network

```
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
}
resource "openstack_networking_floatingip_v2" "fip_1" {
 pool = "my_pool"
}
resource "openstack_compute_floatingip_associate_v2" "fip_1" {
  floating_ip = "${openstack_networking_floatingip_v2.fip_1.address}"
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
}
» Explicitly set the network to attach to
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
 name
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                = 3
 flavor_id
               = "my_key_pair_name"
  key_pair
  security_groups = ["default"]
 network {
   name = "my_network"
 network {
   name = "default"
 }
}
resource "openstack_networking_floatingip_v2" "fip_1" {
 pool = "my_pool"
resource "openstack_compute_floatingip_associate_v2" "fip_1" {
  floating_ip = "${openstack_networking_floatingip_v2.fip_1.address}"
```

```
instance_id = "${openstack_compute_instance_v2.instance_1.id}"
fixed_ip = "${openstack_compute_instance_v2.instance_1.network.1.fixed_ip_v4}"
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new floatingip\_associate.
- floating\_ip (Required) The floating IP to associate.
- instance\_id (Required) The instance to associte the floating IP with.
- fixed\_ip (Optional) The specific IP address to direct traffic to.
- wait\_until\_associated (Optional) In cases where the OpenStack environment does not automatically wait until the association has finished, set this option to have Terraform poll the instance until the floating IP has been associated. Defaults to false.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- floating\_ip See Argument Reference above.
- instance\_id See Argument Reference above.
- fixed\_ip See Argument Reference above.

### » Import

This resource can be imported by specifying all three arguments, separated by a forward slash:

\$ terraform import openstack\_compute\_floatingip\_associate\_v2.fip\_1 <floating\_ip>/<instance\_</pre>

# » openstack\_compute\_instance\_v2

Manages a V2 VM instance resource within OpenStack.

## » Example Usage

#### » Basic Instance

```
resource "openstack_compute_instance_v2" "basic" {
                 = "basic"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                 = "3"
 flavor_id
              = "my_key_pair_name"
 key_pair
  security_groups = ["default"]
 metadata = {
    this = "that"
 network {
   name = "my_network"
}
» Instance With Attached Volume
resource "openstack_blockstorage_volume_v2" "myvol" {
 name = "myvol"
 size = 1
}
resource "openstack_compute_instance_v2" "myinstance" {
                 = "myinstance"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
 flavor_id
                 = "3"
                 = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 network {
   name = "my_network"
 }
}
resource "openstack_compute_volume_attach_v2" "attached" {
  instance_id = "${openstack_compute_instance_v2.myinstance.id}"
  volume_id = "${openstack_blockstorage_volume_v2.myvol.id}"
}
```

### » Boot From Volume

```
resource "openstack_compute_instance_v2" "boot-from-volume" {
                 = "boot-from-volume"
 flavor_id
                 = "3"
                 = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 block_device {
                         = "<image-id>"
   uuid
                         = "image"
   source_type
                         = 5
   volume_size
   boot_index
                         = 0
                     = "volume"
   destination_type
   delete_on_termination = true
 network {
   name = "my_network"
}
» Boot From an Existing Volume
resource "openstack_blockstorage_volume_v1" "myvol" {
          = "myvol"
 name
 size
          = 5
 image_id = "<image-id>"
resource "openstack_compute_instance_v2" "boot-from-volume" {
                = "bootfromvolume"
 name
                = "3"
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 block_device {
                         = "${openstack_blockstorage_volume_v1.myvol.id}"
   uuid
                         = "volume"
   source_type
   boot_index
                         = 0
                         = "volume"
   destination_type
   delete_on_termination = true
 network {
```

```
name = "my_network"
 }
}
» Boot Instance, Create Volume, and Attach Volume as a Block De-
vice
resource "openstack_compute_instance_v2" "instance_1" {
                = "instance_1"
 name
                = "<image-id>"
 image_id
                = "3"
 flavor_id
 key_pair = "my_key_pair_name"
 security_groups = ["default"]
 block_device {
   uuid
                         = "<image-id>"
                        = "image"
   source_type
   destination_type
                        = "local"
   boot_index
   delete_on_termination = true
 }
 block_device {
                         = "blank"
   source_type
   destination_type
                       = "volume"
   volume_size
                         = 1
   boot_index
   delete_on_termination = true
}
» Boot Instance and Attach Existing Volume as a Block Device
resource "openstack_blockstorage_volume_v2" "volume_1" {
 name = "volume_1"
 size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
 name
               = "instance_1"
                = "<image-id>"
 image_id
```

= "my\_key\_pair\_name"

= "3"

security\_groups = ["default"]

flavor\_id

key\_pair

```
block_device {
    uuid
                          = "<image-id>"
                         = "image"
    source_type
    destination_type
                         = "local"
   boot_index
   delete_on_termination = true
 }
 block_device {
                          = "${openstack_blockstorage_volume_v2.volume_1.id}"
   uuid
                          = "volume"
    source_type
                         = "volume"
    destination_type
   boot index
                          = 1
   delete_on_termination = true
}
» Instance With Multiple Networks
resource "openstack_networking_floatingip_v2" "myip" {
 pool = "my_pool"
}
resource "openstack_compute_instance_v2" "multi-net" {
                 = "multi-net"
 name
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                 = "3"
 flavor_id
 key_pair
                 = "my_key_pair_name"
 security_groups = ["default"]
 network {
   name = "my_first_network"
 network {
   name = "my_second_network"
}
resource "openstack_compute_floatingip_associate_v2" "myip" {
  floating_ip = "${openstack_networking_floatingip_v2.myip.address}"
  instance_id = "${openstack_compute_instance_v2.multi-net.id}"
  fixed_ip = "${openstack_compute_instance_v2.multi-net.network.1.fixed_ip_v4}"
}
```

### » Instance With Personality

```
resource "openstack_compute_instance_v2" "personality" {
                 = "personality"
 image_id
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
                = "3"
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 personality {
   file = "/path/to/file/on/instance.txt"
   content = "contents of file"
 }
 network {
   name = "my_network"
}
```

### » Instance with Multiple Ephemeral Disks

```
resource "openstack_compute_instance_v2" "multi-eph" {
                = "multi eph"
 name
                = "ad091b52-742f-469e-8f3c-fd81cadf0743"
 image_id
 flavor_id
                = "3"
 key_pair
                = "my_key_pair_name"
 security_groups = ["default"]
 block_device {
   boot_index
                        = 0
   delete_on_termination = true
   destination_type = "local"
                        = "image"
   source_type
                       = "<image-id>"
   uuid
 }
 block_device {
   boot_index
                        = -1
   delete_on_termination = true
   destination_type = "local"
   source_type
                        = "blank"
   volume_size
                       = 1
 }
 block_device {
```

```
boot_index = -1
delete_on_termination = true
destination_type = "local"
source_type = "blank"
volume_size = 1
}
```

#### » Instance with User Data (cloud-init)

user\_data can come from a variety of sources: inline, read in from the file function, or the template\_cloudinit\_config resource.

## » Argument Reference

}

The following arguments are supported:

- region (Optional) The region in which to create the server instance. If omitted, the region argument of the provider is used. Changing this creates a new server.
- name (Required) A unique name for the resource.
- image\_id (Optional; Required if image\_name is empty and not booting from a volume. Do not specify if booting from a volume.) The image ID of the desired image for the server. Changing this creates a new server.
- image\_name (Optional; Required if image\_id is empty and not booting from a volume. Do not specify if booting from a volume.) The name of the desired image for the server. Changing this creates a new server.
- flavor\_id (Optional; Required if flavor\_name is empty) The flavor ID of the desired flavor for the server. Changing this resizes the existing server.

- flavor\_name (Optional; Required if flavor\_id is empty) The name of the desired flavor for the server. Changing this resizes the existing server.
- user\_data (Optional) The user data to provide when launching the instance. Changing this creates a new server.
- security\_groups (Optional) An array of one or more security group names or ids to associate with the server. Changing this results in adding/removing security groups from the existing server. *Note*: When attaching the instance to networks using Ports, place the security groups on the Port and not the instance.
- availability\_zone (Optional) The availability zone in which to create the server. Changing this creates a new server.
- network (Optional) An array of one or more networks to attach to the instance. The network object structure is documented below. Changing this creates a new server.
- metadata (Optional) Metadata key/value pairs to make available from within the instance. Changing this updates the existing server metadata.
- config\_drive (Optional) Whether to use the config\_drive feature to configure the instance. Changing this creates a new server.
- admin\_pass (Optional) The administrative password to assign to the server. Changing this changes the root password on the existing server.
- key\_pair (Optional) The name of a key pair to put on the server. The key pair must already be created and associated with the tenant's account. Changing this creates a new server.
- block\_device (Optional) Configuration of block devices. The block\_device structure is documented below. Changing this creates a new server. You can specify multiple block devices which will create an instance with multiple disks. This configuration is very flexible, so please see the following reference for more information.
- scheduler\_hints (Optional) Provide the Nova scheduler with hints on how the instance should be launched. The available hints are described below.
- personality (Optional) Customize the personality of an instance by defining one or more files and their contents. The personality structure is described below.
- stop\_before\_destroy (Optional) Whether to try stop instance gracefully before destroying it, thus giving chance for guest OS daemons to stop correctly. If instance doesn't stop within timeout, it will be destroyed anyway.

- force\_delete (Optional) Whether to force the OpenStack instance to be forcefully deleted. This is useful for environments that have reclaim / soft deletion enabled.
- power\_state (Optional) Provide the VM state. Only 'active' and 'shutoff' are supported values. *Note*: If the initial power\_state is the shutoff
  the VM will be stopped immediately after build and the provisioners like
  remote-exec or files are not supported.
- tags (Optional) A set of string tags for the instance. Changing this updates the existing instance tags.
- vendor\_options (Optional) Map of additional vendor-specific options. Supported options are described below.

#### The network block supports:

- uuid (Required unless port or name is provided) The network UUID to attach to the server. Changing this creates a new server.
- name (Required unless unid or port is provided) The human-readable name of the network. Changing this creates a new server.
- port (Required unless unid or name is provided) The port UUID of a network to attach to the server. Changing this creates a new server.
- fixed\_ip\_v4 (Optional) Specifies a fixed IPv4 address to be used on this network. Changing this creates a new server.
- access\_network (Optional) Specifies if this network should be used for provisioning access. Accepts true or false. Defaults to false.

#### The block\_device block supports:

- uuid (Required unless source\_type is set to "blank" ) The UUID of the image, volume, or snapshot. Changing this creates a new server.
- source\_type (Required) The source type of the device. Must be one of "blank", "image", "volume", or "snapshot". Changing this creates a new server.
- volume\_size The size of the volume to create (in gigabytes). Required in the following combinations: source=image and destination=volume, source=blank and destination=local, and source=blank and destination=volume. Changing this creates a new server.
- boot\_index (Optional) The boot index of the volume. It defaults to 0. Changing this creates a new server.
- destination\_type (Optional) The type that gets created. Possible values are "volume" and "local". Changing this creates a new server.

- delete\_on\_termination (Optional) Delete the volume / block device upon termination of the instance. Defaults to false. Changing this creates a new server.
- volume\_type (Optional) The volume type that will be used, for example SSD or HDD storage. The available options depend on how your specific OpenStack cloud is configured and what classes of storage are provided. Changing this creates a new server.
- device\_type (Optional) The low-level device type that will be used.
   Most common thing is to leave this empty. Changing this creates a new server.
- disk\_bus (Optional) The low-level disk bus that will be used. Most common thing is to leave this empty. Changing this creates a new server.

#### The scheduler hints block supports:

- group (Optional) A UUID of a Server Group. The instance will be placed into that group.
- different\_host (Optional) A list of instance UUIDs. The instance will be scheduled on a different host than all other instances.
- same\_host (Optional) A list of instance UUIDs. The instance will be scheduled on the same host of those specified.
- query (Optional) A conditional query that a compute node must pass in order to host an instance. The query must use the JsonFilter syntax which is described here. At this time, only simple queries are supported. Compound queries using and, or, or not are not supported. An example of a simple query is:

```
[">=", "$free_ram_mb", "1024"]
```

- target\_cell (Optional) The name of a cell to host the instance.
- build\_near\_host\_ip (Optional) An IP Address in CIDR form. The instance will be placed on a compute node that is in the same subnet.
- additional\_properties (Optional) Arbitrary key/value pairs of additional properties to pass to the scheduler.

## The personality block supports:

- file (Required) The absolute path of the destination file.
- content (Required) The contents of the file. Limited to 255 bytes.

#### The vendor\_options block supports:

• ignore\_resize\_confirmation - (Optional) Boolean to control whether to ignore manual confirmation of the instance resizing. This can be helpful

to work with some OpenStack clouds which automatically confirm resizing of instances after some timeout.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- access\_ip\_v4 The first detected Fixed IPv4 address.
- access\_ip\_v6 The first detected Fixed IPv6 address.
- metadata See Argument Reference above.
- security\_groups See Argument Reference above.
- flavor\_id See Argument Reference above.
- flavor\_name See Argument Reference above.
- network/uuid See Argument Reference above.
- network/name See Argument Reference above.
- network/port See Argument Reference above.
- network/fixed\_ip\_v4 The Fixed IPv4 address of the Instance on that network.
- network/fixed\_ip\_v6 The Fixed IPv6 address of the Instance on that network.
- network/mac The MAC address of the NIC on that network.
- all\_metadata Contains all instance metadata, even metadata not set by Terraform.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the instance, which have been explicitly and implicitly added.

### » Notes

#### » Multiple Ephemeral Disks

It's possible to specify multiple block\_device entries to create an instance with multiple ephemeral (local) disks. In order to create multiple ephemeral disks, the sum of the total amount of ephemeral space must be less than or equal to what the chosen flavor supports.

The following example shows how to create an instance with multiple ephemeral disks:

```
block_device {
   boot_index
                         = 0
   delete_on_termination = true
                        = "local"
   destination_type
   source_type
                         = "image"
                         = "<image uuid>"
   uuid
 }
 block_device {
   boot_index
                         = -1
   delete_on_termination = true
                       = "local"
   destination_type
                        = "blank"
   source_type
   volume size
                         = 1
 }
 block_device {
                         = -1
   boot_index
   delete_on_termination = true
   destination_type = "local"
   source_type
                         = "blank"
   volume_size
                         = 1
}
```

## » Instances and Security Groups

When referencing a security group resource in an instance resource, always use the *name* of the security group. If you specify the ID of the security group, Terraform will remove and reapply the security group upon each call. This is because the OpenStack Compute API returns the names of the associated security groups and not their IDs.

Note the following example:

```
resource "openstack_networking_secgroup_v2" "sg_1" {
   name = "sg_1"
}

resource "openstack_compute_instance_v2" "foo" {
   name = "terraform-test"
   security_groups = ["${openstack_networking_secgroup_v2.sg_1.name}"]
}
```

#### » Instances and Ports

Neutron Ports are a great feature and provide a lot of functionality. However, there are some notes to be aware of when mixing Instances and Ports:

- In OpenStack environments prior to the Kilo release, deleting or recreating an Instance will cause the Instance's Port(s) to be deleted. One way of working around this is to taint any Port(s) used in Instances which are to be recreated. See here for further information.
- When attaching an Instance to one or more networks using Ports, place the security groups on the Port and not the Instance. If you place the security groups on the Instance, the security groups will not be applied upon creation, but they will be applied upon a refresh. This is a known OpenStack bug.
- Network IP information is not available within an instance for networks that are attached with Ports. This is mostly due to the flexibility Neutron Ports provide when it comes to IP addresses. For example, a Neutron Port can have multiple Fixed IP addresses associated with it. It's not possible to know which single IP address the user would want returned to the Instance's state information. Therefore, in order for a Provisioner to connect to an Instance via it's network Port, customize the connection information:

```
resource "openstack_networking_port_v2" "port_1" {
                 = "port 1"
  admin_state_up = "true"
 network_id = "0a1d0a27-cffa-4de3-92c5-9d3fd3f2e74d"
  security_group_ids = [
    "2f02d20a-8dca-49b7-b26f-b6ce9fddaf4f",
    "ca1e5ed7-dae8-4605-987b-fadaeeb30461",
 ]
}
resource "openstack_compute_instance_v2" "instance_1" {
 name = "instance 1"
 network {
   port = "${openstack_networking_port_v2.port_1.id}"
  connection {
                = "root"
    user
    host.
                = "${openstack_networking_port_v2.port_1.fixed_ip.0.ip_address}"
```

```
private_key = "~/path/to/key"
}

provisioner "remote-exec" {
  inline = [
    "echo terraform executed > /tmp/foo",
  ]
}
```

#### » Instances and Networks

Instances almost always require a network. Here are some notes to be aware of with how Instances and Networks relate:

- In scenarios where you only have one network available, you can create an instance without specifying a **network** block. OpenStack will automatically launch the instance on this network.
- If you have access to more than one network, you will need to specify a
  network with a network block. Not specifying a network will result in the
  following error:
- \* openstack\_compute\_instance\_v2.instance: Error creating OpenStack server: Expected HTTP response code [201 202] when accessing [POST https://example.com:8774/v2.1/set {"conflictingRequest": {"message": "Multiple possible networks found, use a Network ID to be
  - If you intend to use the openstack\_compute\_interface\_attach\_v2 resource, you still need to make sure one of the above points is satisfied. An instance cannot be created without a valid network configuration even if you intend to use openstack\_compute\_interface\_attach\_v2 after the instance has been created.

## » Importing instances

Importing instances can be tricky, since the nova api does not offer all information provided at creation time for later retrieval. Network interface attachment order, and number and sizes of ephemeral disks are examples of this.

#### » Importing basic instance

Assume you want to import an instance with one ephemeral root disk, and one network interface.

Your configuration would look like the following:

Then you execute terraform import openstack\_compute\_instance\_v2.basic\_instance <instance\_id>

## » Importing an instance with multiple emphemeral disks

The importer cannot read the emphemeral disk configuration of an instance, so just specify image\_id as in the configuration of the basic instance example.

#### » Importing instance with multiple network interfaces.

Nova returns the network interfaces grouped by network, thus not in creation order. That means that if you have multiple network interfaces you must take care of the order of networks in your configuration.

As example we want to import an instance with one ephemeral root disk, and 3 network interfaces.

#### Examples

```
resource "openstack_compute_instance_v2" "boot-from-volume" {
                = "boot-from-volume"
 name
               = "<flavor_id"
 flavor_id
               = "<keyname>"
 key_pair
             = <image_id>
 image_id
 security_groups = ["default"]
 network {
   name = "<network1>"
 network {
   name = "<netowork2>"
 network {
   name = "<network1>"
```

```
fixed_ip_v4 = "<fixed_ip_v4>"
}
```

In the above configuration the networks are out of order compared to what nova and thus the import code returns, which means the plan will not be empty after import.

So either with care check the plan and modify configuration, or read the network order in the state file after import and modify your configuration accordingly.

• A note on ports. If you have created a neutron port independent of an instance, then the import code has no way to detect that the port is created idenpendently, and therefore on deletion of imported instances you might have port resources in your project, which you expected to be created by the instance and thus to also be deleted with the instance.

#### » Importing instances with multiple block storage volumes.

We have an instance with two block storage volumes, one bootable and one non-bootable. Note that we only configure the bootable device as block\_device. The other volumes can be specified as openstack\_blockstorage\_volume\_v2

```
resource "openstack_compute_instance_v2" "instance_2" {
                  = "instance 2"
 name
  image_id
                  = "<image_id>"
  flavor_id
                  = "<flavor_id>"
                  = "<keyname>"
 key_pair
  security_groups = ["default"]
 block_device {
   uuid = <image id>"
    source_type = "image"
    destination_type = "volume"
   boot index = 0
    delete on termination = true
 }
   network {
   name = "<network_name>"
 }
}
resource "openstack_blockstorage_volume_v2" "volume_1" {
  size
             "<vol_name>"
  name =
}
```

```
resource "openstack_compute_volume_attach_v2" "va_1" {
   volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
   instance_id = "${openstack_compute_instance_v2.instance_2.id}"
}
```

To import the instance outlined in the above configuration do the following:

terraform import openstack\_compute\_instance\_v2.instance\_2 <instance\_id>
import openstack\_blockstorage\_volume\_v2.volume\_1 <volume\_id>
terraform import openstack\_compute\_volume\_attach\_v2.va\_1
<instance\_id>/<volume\_id>

• A note on block storage volumes, the importer does not read delete\_on\_termination flag, and always assumes true. If you import an instance created with delete\_on\_termination false, you end up with "orphaned" volumes after destruction of instances.

# » openstack\_compute\_interface\_attach\_v2

Attaches a Network Interface (a Port) to an Instance using the OpenStack Compute (Nova) v2 API.

## » Example Usage

#### » Basic Attachment

#### » Attachment Specifying a Fixed IP

```
resource "openstack_networking_network_v2" "network_1" {
```

```
= "network_1"
 name
  admin_state_up = "true"
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
  security_groups = ["default"]
}
resource "openstack_compute_interface_attach_v2" "ai_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
 network_id = "${openstack_networking_port_v2.network_1.id}"
            = "10.0.10.10"
 fixed_ip
}
» Attachment Using an Existing Port
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_port_v2" "port_1" {
                = "port_1"
 network_id
                = "${openstack_networking_network_v2.network_1.id}"
  admin_state_up = "true"
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance 1"
  security_groups = ["default"]
resource "openstack_compute_interface_attach_v2" "ai_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
 port_id
            = "${openstack_networking_port_v2.port_1.id}"
}
» Attaching Multiple Interfaces
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
```

```
}
resource "openstack_networking_port_v2" "ports" {
                 = 2
  count
 name
                 = "${format("port-%02d", count.index + 1)}"
                 = "${openstack_networking_network_v2.network_1.id}"
 network_id
  admin_state_up = "true"
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance 1"
  security_groups = ["default"]
}
resource "openstack_compute_interface_attach_v2" "attachments" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
             = "${openstack_networking_port_v2.ports.*.id[count.index]}"
 port_id
}
Note that the above example will not guarantee that the ports are attached in a
deterministic manner. The ports will be attached in a seemingly random order.
If you want to ensure that the ports are attached in a given order, create explicit
dependencies between the ports, such as:
resource "openstack_networking_network_v2" "network_1" {
                 = "network 1"
  admin_state_up = "true"
}
resource "openstack_networking_port_v2" "ports" {
  count
                 = "${format("port-%02d", count.index + 1)}"
 name
 network id
                 = "${openstack_networking_network_v2.network_1.id}"
  admin_state_up = "true"
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance_1"
  security_groups = ["default"]
}
resource "openstack_compute_interface_attach_v2" "ai_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
             = "${openstack networking port v2.ports.*.id[0]}"
}
```

```
resource "openstack_compute_interface_attach_v2" "ai_2" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  port_id = "${openstack_networking_port_v2.ports.*.id[1]}"
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the interface attachment. If omitted, the region argument of the provider is used. Changing this creates a new attachment.
- instance\_id (Required) The ID of the Instance to attach the Port or Network to.
- port\_id (Optional) The ID of the Port to attach to an Instance. *NOTE*: This option and network\_id are mutually exclusive.
- network\_id (Optional) The ID of the Network to attach to an Instance.
   A port will be created automatically. NOTE: This option and port\_id are mutually exclusive.
- fixed\_ip (Optional) An IP address to assosciate with the port. NOTE: This option cannot be used with port\_id. You must specify a network\_id. The IP address must lie in a range on the supplied network.

## » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- instance\_id See Argument Reference above.
- port\_id See Argument Reference above.
- network\_id See Argument Reference above.
- fixed\_ip See Argument Reference above.

## » Import

Interface Attachments can be imported using the Instance ID and Port ID separated by a slash, e.g.

\$ terraform import openstack\_compute\_interface\_attach\_v2.ai\_1 89c60255-9bd6-460c-822a-e2b95

# » openstack\_compute\_keypair\_v2

Manages a V2 keypair resource within OpenStack.

Important Security Notice The private key generated by this resource will be stored *unencrypted* in your Terraform state file. Use of this resource for production deployments is *not* recommended. Instead, generate a private key file outside of Terraform and distribute it securely to the system where Terraform will be run.

## » Example Usage

#### » Import an Existing Public Key

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new keypair.
- name (Required) A unique name for the keypair. Changing this creates a new keypair.
- public\_key (Optional) A pregenerated OpenSSH-formatted public key. Changing this creates a new keypair. If a public key is not specified, then a public/private key pair will be automatically generated. If a pair is created, then destroying this resource means you will lose access to that keypair forever.
- value\_specs (Optional) Map of additional options.

## » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- public\_key See Argument Reference above.
- fingerprint The fingerprint of the public key.
- private\_key The generated private key when no public key is specified.

## » Import

Keypairs can be imported using the name, e.g.

\$ terraform import openstack\_compute\_keypair\_v2.my-keypair test-keypair

# » openstack\_compute\_secgroup\_v2

Manages a V2 security group resource within OpenStack.

Please note that managing security groups through the OpenStack Compute API has been deprecated. Unless you are using an older OpenStack environment, it is recommended to use the openstack\_networking\_secgroup\_v2 and openstack\_networking\_secgroup\_rule\_v2 resources instead, which uses the OpenStack Networking API.

## » Example Usage

} }

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a security group. If omitted, the region argument of the provider is used. Changing this creates a new security group.
- name (Required) A unique name for the security group. Changing this updates the name of an existing security group.
- description (Required) A description for the security group. Changing this updates the description of an existing security group.
- rule (Optional) A rule describing how the security group operates. The rule object structure is documented below. Changing this updates the security group rules. As shown in the example above, multiple rule blocks may be used.

#### The rule block supports:

- from\_port (Required) An integer representing the lower bound of the port range to open. Changing this creates a new security group rule.
- to\_port (Required) An integer representing the upper bound of the port range to open. Changing this creates a new security group rule.
- ip\_protocol (Required) The protocol type that will be allowed. Changing this creates a new security group rule.
- cidr (Optional) Required if from\_group\_id or self is empty. The IP range that will be the source of network traffic to the security group. Use 0.0.0.0/0 to allow all IP addresses. Changing this creates a new security group rule. Cannot be combined with from\_group\_id or self.
- from\_group\_id (Optional) Required if cidr or self is empty. The ID of a group from which to forward traffic to the parent group. Changing this creates a new security group rule. Cannot be combined with cidr or self.
- self (Optional) Required if cidr and from\_group\_id is empty. If true, the security group itself will be added as a source to this ingress rule. Cannot be combined with cidr or from\_group\_id.

## » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- rule See Argument Reference above.

## » Notes

#### » ICMP Rules

When using ICMP as the ip\_protocol, the from\_port sets the ICMP type and the to\_port sets the ICMP code. To allow all ICMP types, set each value to -1, like so:

```
rule {
   from_port = -1
   to_port = -1
   ip_protocol = "icmp"
   cidr = "0.0.0.0/0"
}
```

A list of ICMP types and codes can be found here.

#### » Referencing Security Groups

When referencing a security group in a configuration (for example, a configuration creates a new security group and then needs to apply it to an instance being created in the same configuration), it is currently recommended to reference the security group by name and not by ID, like this:

## » Import

Security Groups can be imported using the id, e.g.

\$ terraform import openstack\_compute\_secgroup\_v2.my\_secgroup 1bc30ee9-9d5b-4c30-bdd5-7f1e66

# » openstack\_compute\_servergroup\_v2

Manages a V2 Server Group resource within OpenStack.

## » Example Usage

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used. Changing this creates a new server group.
- name (Required) A unique name for the server group. Changing this creates a new server group.
- policies (Required) The set of policies for the server group. All policies are mutually exclusive. See the Policies section for more information. Changing this creates a new server group.
- value\_specs (Optional) Map of additional options.

#### » Policies

- affinity All instances/servers launched in this group will be hosted on the same compute node.
- anti-affinity All instances/servers launched in this group will be hosted on different compute nodes.
- soft-affinity All instances/servers launched in this group will be hosted on the same compute node if possible, but if not possible they still will be scheduled instead of failure. To use this policy your OpenStack environment should support Compute service API 2.15 or above.
- soft-anti-affinity All instances/servers launched in this group will be hosted on different compute nodes if possible, but if not possible they still will be scheduled instead of failure. To use this policy your OpenStack environment should support Compute service API 2.15 or above.

## » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- policies See Argument Reference above.
- members The instances that are part of this server group.

## » Import

Server Groups can be imported using the id, e.g.

\$ terraform import openstack\_compute\_servergroup\_v2.test-sg 1bc30ee9-9d5b-4c30-bdd5-7f1e663

# » openstack\_compute\_quotaset\_v2

Manages a V2 compute quotaset resource within OpenStack.

Note: This usually requires admin privileges.

**Note:** This resource has a no-op deletion so no actual actions will be done against the OpenStack API in case of delete call.

## » Example Usage

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new quotaset.
- project\_id (Required) ID of the project to manage quotas. Changing this creates a new quotaset.
- fixed\_ips (Optional) Quota value for fixed IPs. Changing this updates the existing quotaset.
- floating\_ips (Optional) Quota value for floating IPs. Changing this updates the existing quotaset.
- injected\_file\_content\_bytes (Optional) Quota value for content bytes of injected files. Changing this updates the existing quotaset.
- injected\_file\_path\_bytes (Optional) Quota value for path bytes of injected files. Changing this updates the existing quotaset.
- injected\_files (Optional) Quota value for injected files. Changing this updates the existing quotaset.
- key\_pairs (Optional) Quota value for key pairs. Changing this updates the existing quotaset.
- metadata\_items (Optional) Quota value for metadata items. Changing this updates the existing quotaset.
- ram (Optional) Quota value for RAM. Changing this updates the existing quotaset.
- security\_group\_rules (Optional) Quota value for security group rules. Changing this updates the existing quotaset.
- security\_groups (Optional) Quota value for security groups. Changing this updates the existing quotaset.
- cores (Optional) Quota value for cores. Changing this updates the existing quotaset.
- instances (Optional) Quota value for instances. Changing this updates the existing quotaset.
- server\_groups (Optional) Quota value for server groups. Changing this updates the existing quotaset.
- server\_group\_members (Optional) Quota value for server groups members. Changing this updates the existing quotaset.

#### » Attributes Reference

- region See Argument Reference above.
- project\_id See Argument Reference above.
- fixed\_ips See Argument Reference above.
- floating\_ips See Argument Reference above.
- injected\_file\_content\_bytes See Argument Reference above.
- injected\_file\_path\_bytes See Argument Reference above.
- injected\_files See Argument Reference above.
- key\_pairs See Argument Reference above.
- metadata\_items See Argument Reference above.
- ram See Argument Reference above.
- security\_group\_rules See Argument Reference above.
- security\_groups See Argument Reference above.
- cores See Argument Reference above.
- instances See Argument Reference above.
- server\_groups See Argument Reference above.
- server\_group\_members See Argument Reference above.

## » Import

Quotasets can be imported using the project\_id, e.g.

\$ terraform import openstack\_compute\_quotaset\_v2.quotaset\_1 2a0f2240-c5e6-41de-896d-e80d974

# ${\tt "openstack\_compute\_volume\_attach\_v2}$

Attaches a Block Storage Volume to an Instance using the OpenStack Compute (Nova) v2 API.

## » Example Usage

» Basic attachment of a single volume to a single instance

```
instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
}
» Attaching multiple volumes to a single instance
resource "openstack_blockstorage_volume_v2" "volumes" {
 name = "${format("vol-%02d", count.index + 1)}"
  size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance 1"
  security_groups = ["default"]
}
resource "openstack compute volume attach v2" "attachments" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volumes.*.id[count.index]}"
output "volume devices" {
  value = "${openstack_compute_volume_attach_v2.attachments.*.device}"
Note that the above example will not guarantee that the volumes are attached
in a deterministic manner. The volumes will be attached in a seemingly random
order.
If you want to ensure that the volumes are attached in a given order, create
explicit dependencies between the volumes, such as:
resource "openstack_blockstorage_volume_v2" "volumes" {
 name = "${format("vol-%02d", count.index + 1)}"
  size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance 1"
  security_groups = ["default"]
}
resource "openstack_compute_volume_attach_v2" "attach_1" {
```

```
instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volumes.0.id}"
}

resource "openstack_compute_volume_attach_v2" "attach_2" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volumes.1.id}"
  depends_on = ["openstack_compute_volume_attach_v2.attach_1"]
}

output "volume devices" {
  value = "${openstack_compute_volume_attach_v2.attachments.*.device}"
}
```

## » Using Multiattach-enabled volumes

Multiattach Volumes are dependent upon your OpenStack cloud and not all clouds support multiattach.

```
resource "openstack_blockstorage_volume_v3" "volume_1" {
             = "volume_1"
 size
 multiattach = true
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
  security_groups = ["default"]
resource "openstack_compute_instance_v2" "instance_2" {
                 = "instance_2"
  security_groups = ["default"]
}
resource "openstack_compute_volume_attach_v2" "va_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
             = "${openstack_blockstorage_volume_v2.volume_1.id}"
 multiattach = true
}
resource "openstack_compute_volume_attach_v2" "va_2" {
  instance_id = "${openstack_compute_instance_v2.instance_2.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
```

```
multiattach = true

depends_on = ["openstack_compute_volume_attach_v2.va_1"]
}
```

It is recommended to use depends\_on for the attach resources to enforce the volume attachments to happen one at a time.

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- instance\_id (Required) The ID of the Instance to attach the Volume to.
- volume\_id (Required) The ID of the Volume to attach to an Instance.
- device (Optional) The device of the volume attachment (ex: /dev/vdc). NOTE: Being able to specify a device is dependent upon the hypervisor in use. There is a chance that the device specified in Terraform will not be the same device the hypervisor chose. If this happens, Terraform will wish to update the device upon subsequent applying which will cause the volume to be detached and reattached indefinitely. Please use with caution.
- multiattach (Optional) Enable attachment of multiattach-capable volumes.

#### » Attributes Reference

- region See Argument Reference above.
- instance\_id See Argument Reference above.
- volume\_id See Argument Reference above.
- device See Argument Reference above. *NOTE*: The correctness of this information is dependent upon the hypervisor in use. In some cases, this should not be used as an authoritative piece of information.
- multiattach See Argument Reference above.

## » Import

Volume Attachments can be imported using the Instance ID and Volume ID separated by a slash, e.g.

\$ terraform import openstack\_compute\_volume\_attach\_v2.va\_1 89c60255-9bd6-460c-822a-e2b959ede

# » openstack containerinfra cluster v1

Manages a V1 Magnum cluster resource within OpenStack.

## » Example Usage

#### » Create a Cluster

## » Argument reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 Container Infra client. A Container Infra client is needed to create a cluster. If omitted, the region argument of the provider is used. Changing this creates a new cluster.
- name (Required) The name of the cluster. Changing this updates the name of the existing cluster template.
- project\_id (Optional) The project of the cluster. Required if admin wants to create a cluster in another project. Changing this creates a new cluster.
- user\_id (Optional) The user of the cluster. Required if admin wants to create a cluster template for another user. Changing this creates a new cluster.
- cluster\_template\_id (Required) The UUID of the V1 Container Infra cluster template. Changing this creates a new cluster.

- create\_timeout (Optional) The timeout (in minutes) for creating the cluster. Changing this creates a new cluster.
- discovery\_url (Optional) The URL used for cluster node discovery. Changing this creates a new cluster.
- docker\_volume\_size (Optional) The size (in GB) of the Docker volume. Changing this creates a new cluster.
- flavor (Optional) The flavor for the nodes of the cluster. Can be set via the OS\_MAGNUM\_FLAVOR environment variable. Changing this creates a new cluster.
- master\_flavor (Optional) The flavor for the master nodes. Can be set via the OS\_MAGNUM\_MASTER\_FLAVOR environment variable. Changing this creates a new cluster.
- keypair (Optional) The name of the Compute service SSH keypair. Changing this creates a new cluster.
- labels (Optional) The list of key value pairs representing additional properties of the cluster. Changing this creates a new cluster.
- master\_count (Optional) The number of master nodes for the cluster. Changing this creates a new cluster.
- node\_count (Optional) The number of nodes for the cluster. Changing this creates a new cluster.
- fixed\_network (Optional) The fixed network that will be attached to the cluster. Changing this creates a new cluster.
- fixed\_subnet (Optional) The fixed subnet that will be attached to the cluster. Changing this creates a new cluster.

#### » Attributes reference

- region See Argument Reference above.
- name See Argument Reference above.
- project\_id See Argument Reference above.
- created\_at The time at which cluster was created.
- updated\_at The time at which cluster was created.
- api\_address COE API address.
- coe\_version COE software version.
- cluster\_template\_id See Argument Reference above.
- container\_version Container software version.
- create timeout See Argument Reference above.
- discovery url See Argument Reference above.

- docker\_volume\_size See Argument Reference above.
- flavor See Argument Reference above.
- master\_flavor See Argument Reference above.
- keypair See Argument Reference above.
- labels See Argument Reference above.
- master\_count See Argument Reference above.
- node\_count See Argument Reference above.
- fixed\_network See Argument Reference above.
- fixed\_subnet See Argument Reference above.
- master\_addresses IP addresses of the master node of the cluster.
- node\_addresses IP addresses of the node of the cluster.
- stack\_id UUID of the Orchestration service stack.

## » Import

Clusters can be imported using the id, e.g.

\$ terraform import openstack\_containerinfra\_cluster\_v1.cluster\_1 ce0f9463-dd25-474b-9fe8-946

# » openstack\_containerinfra\_clustertemplate\_v1

Manages a V1 Magnum cluster template resource within OpenStack.

## » Example Usage

#### » Create a Cluster template

```
resource "openstack_containerinfra_clustertemplate_v1" "clustertemplate_1" {
                        = "clustertemplate_1"
  name
                        = "Fedora-Atomic-27"
  image
                        = "kubernetes"
  coe
                        = "m1.small"
 flavor
                        = "m1.medium"
 master_flavor
                        = "1.1.1.1"
  dns_nameserver
  docker_storage_driver = "devicemapper"
  docker_volume_size
                        = 10
  volume driver
                        = "cinder"
 network_driver
                        = "flannel"
  server_type
                        = "vm"
 master_lb_enabled
                        = true
  floating_ip_enabled
                        = false
  labels = {
```

## » Argument reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 Container Infra client. A Container Infra client is needed to create a cluster template. If omitted, the region argument of the provider is used. Changing this creates a new cluster template.
- name (Required) The name of the cluster template. Changing this updates the name of the existing cluster template.
- project\_id (Optional) The project of the cluster template. Required if admin wants to create a cluster template in another project. Changing this creates a new cluster template.
- user\_id (Optional) The user of the cluster template. Required if admin wants to create a cluster template for another user. Changing this creates a new cluster template.
- apiserver\_port (Optional) The API server port for the Container Orchestration Engine for this cluster template. Changing this updates the API server port of the existing cluster template.
- coe (Required) The Container Orchestration Engine for this cluster template. Changing this updates the engine of the existing cluster template.
- cluster\_distro (Optional) The distro for the cluster (fedora-atomic, coreos, etc.). Changing this updates the cluster distro of the existing cluster template.
- dns\_nameserver (Optional) Address of the DNS nameserver that is used in nodes of the cluster. Changing this updates the DNS nameserver of the existing cluster template.
- docker\_storage\_driver (Optional) Docker storage driver. Changing this updates the Docker storage driver of the existing cluster template.
- docker\_volume\_size (Optional) The size (in GB) of the Docker volume. Changing this updates the Docker volume size of the existing cluster template.

- external\_network\_id (Optional) The ID of the external network that will be used for the cluster. Changing this updates the external network ID of the existing cluster template.
- fixed\_network (Optional) The fixed network that will be attached to the cluster. Changing this updates the fixed network of the existing cluster template.
- fixed\_subnet (Optional) The fixed subnet that will be attached to the cluster. Changing this updates the fixed subnet of the existing cluster template.
- flavor (Optional) The flavor for the nodes of the cluster. Can be set via the OS\_MAGNUM\_FLAVOR environment variable. Changing this updates the flavor of the existing cluster template.
- master\_flavor (Optional) The flavor for the master nodes. Can be set via the OS\_MAGNUM\_MASTER\_FLAVOR environment variable. Changing this updates the master flavor of the existing cluster template.
- floating\_ip\_enabled (Optional) Indicates whether created cluster should create floating IP for every node or not. Changing this updates the floating IP enabled attribute of the existing cluster template.
- http\_proxy (Optional) The address of a proxy for receiving all HTTP requests and relay them. Changing this updates the HTTP proxy address of the existing cluster template.
- https\_proxy (Optional) The address of a proxy for receiving all HTTPS
  requests and relay them. Changing this updates the HTTPS proxy address
  of the existing cluster template.
- image (Required) The reference to an image that is used for nodes of the cluster. Can be set via the OS\_MAGNUM\_IMAGE environment variable. Changing this updates the image attribute of the existing cluster template.
- insecure\_registry (Optional) The insecure registry URL for the cluster template. Changing this updates the insecure registry attribute of the existing cluster template.
- keypair\_id (Optional) The name of the Compute service SSH keypair. Changing this updates the keypair of the existing cluster template.
- labels (Optional) The list of key value pairs representing additional properties of the cluster template. Changing this updates the labels of the existing cluster template.
- master\_lb\_enabled (Optional) Indicates whether created cluster should has a loadbalancer for master nodes or not. Changing this updates the attribute of the existing cluster template.

- network\_driver (Optional) The name of the driver for the container network. Changing this updates the network driver of the existing cluster template.
- no\_proxy (Optional) A comma-separated list of IP addresses that shouldn't be used in the cluster. Changing this updates the no proxy list of the existing cluster template.
- public (Optional) Indicates whether cluster template should be public. Changing this updates the public attribute of the existing cluster template.
- registry\_enabled (Optional) Indicates whether Docker registry is enabled in the cluster. Changing this updates the registry enabled attribute of the existing cluster template.
- server\_type (Optional) The server type for the cluster template. Changing this updates the server type of the existing cluster template.
- tls\_disabled (Optional) Indicates whether the TLS should be disabled in the cluster. Changing this updates the attribute of the existing cluster.
- volume\_driver (Optional) The name of the driver that is used for the volumes of the cluster nodes. Changing this updates the volume driver of the existing cluster template.

#### » Attributes reference

- region See Argument Reference above.
- name See Argument Reference above.
- project\_id See Argument Reference above.
- created at The time at which cluster template was created.
- updated\_at The time at which cluster template was created.
- apiserver\_port See Argument Reference above.
- coe See Argument Reference above.
- cluster\_distro See Argument Reference above.
- dns\_nameserver See Argument Reference above.
- docker\_storage\_driver See Argument Reference above.
- docker\_volume\_size See Argument Reference above.
- external\_network\_id See Argument Reference above.
- fixed\_network See Argument Reference above.
- fixed\_subnet See Argument Reference above.
- flavor See Argument Reference above.
- master\_flavor See Argument Reference above.
- floating\_ip\_enabled See Argument Reference above.
- http proxy See Argument Reference above.
- https proxy See Argument Reference above.

- image See Argument Reference above.
- insecure\_registry See Argument Reference above.
- keypair\_id See Argument Reference above.
- labels See Argument Reference above.
- links A list containing associated cluster template links.
- master\_lb\_enabled See Argument Reference above.
- network\_driver See Argument Reference above.
- no\_proxy See Argument Reference above.
- public See Argument Reference above.
- registry\_enabled See Argument Reference above.
- server\_type See Argument Reference above.
- tls\_disabled See Argument Reference above.
- volume\_driver See Argument Reference above.

## » Import

Cluster templates can be imported using the id, e.g.

\$ terraform import openstack\_containerinfra\_clustertemplate\_v1.clustertemplate\_1 b9a45c5c-co

# » openstack\_db\_instance\_v1

Manages a V1 DB instance resource within OpenStack.

## » Example Usage

#### » Instance

```
resource "openstack_db_instance_v1" "test" {
           = "region-test"
 region
            = "test"
 name
 flavor_id = "31792d21-c355-4587-9290-56c1ed0ca376"
  size
            = 8
 network {
   uuid = "c0612505-caf2-4fb0-b7cb-56a0240a2b12"
  datastore {
    version = "mysql-5.7"
    type
         = "mysql"
 }
}
```

## » Argument Reference

The following arguments are supported:

- region (Required) The region in which to create the db instance. Changing this creates a new instance.
- name (Required) A unique name for the resource.
- flavor\_id (Required) The flavor ID of the desired flavor for the instance. Changing this creates new instance.
- configuration\_id (Optional) Configuration ID to be attached to the instance. Database instance will be rebooted when configuration is detached.
- size (Required) Specifies the volume size in GB. Changing this creates new instance.
- datastore (Required) An array of database engine type and version. The datastore object structure is documented below. Changing this creates a new instance.
- network (Optional) An array of one or more networks to attach to the instance. The network object structure is documented below. Changing this creates a new instance.
- user (Optional) An array of username, password, host and databases. The user object structure is documented below.
- database (Optional) An array of database name, charset and collate. The database object structure is documented below.

#### The datastore block supports:

- type (Required) Database engine type to be used in new instance. Changing this creates a new instance.
- version (Required) Version of database engine type to be used in new instance. Changing this creates a new instance.

#### The network block supports:

- uuid (Required unless port is provided) The network UUID to attach to the instance. Changing this creates a new instance.
- port (Required unless uuid is provided) The port UUID of a network to attach to the instance. Changing this creates a new instance.
- fixed\_ip\_v4 (Optional) Specifies a fixed IPv4 address to be used on this network. Changing this creates a new instance.
- fixed\_ip\_v6 (Optional) Specifies a fixed IPv6 address to be used on this network. Changing this creates a new instance.

## The user block supports:

- name (Optional) Username to be created on new instance. Changing this
  creates a new instance.
- password (Optional) User's password. Changing this creates a new instance.
- host (Optional) An ip address or % sign indicating what ip addresses can connect with this user credentials. Changing this creates a new instance.
- databases (Optional) A list of databases that user will have access to. If not specified, user has access to all databases on the instance. Changing this creates a new instance.

#### The database block supports:

- name (Optional) Database to be created on new instance. Changing this
  creates a new instance.
- collate (Optional) Database collation. Changing this creates a new instance.
- charset (Optional) Database character set. Changing this creates a new instance.

#### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- size See Argument Reference above.
- flavor\_id See Argument Reference above.
- ${\tt configuration\_id}$  See Argument Reference above.
- datastore/type See Argument Reference above.
- datastore/version See Argument Reference above.
- network/uuid See Argument Reference above.
- network/port See Argument Reference above.
- network/fixed\_ip\_v4 The Fixed IPv4 address of the Instance on that network.
- network/fixed\_ip\_v6 The Fixed IPv6 address of the Instance on that
- database/name See Argument Reference above.
- database/collate See Argument Reference above.
- database/charset See Argument Reference above.
- user/name See Argument Reference above.
- user/password See Argument Reference above.
- user/databases See Argument Reference above.
- user/host See Argument Reference above.

# » openstack\_db\_database\_v1

Manages a V1 DB database resource within OpenStack.

## » Example Usage

#### » Database

## » Argument Reference

The following arguments are supported:

- name (Required) A unique name for the resource.
- instance\_id (Required) The ID for the database instance.

## » Attributes Reference

The following attributes are exported:

- region Openstack region resource is created in.
- name See Argument Reference above.
- instance\_id See Argument Reference above.

## » Import

Databases can be imported by using instance-id/db-name, e.g.

\$ terraform import openstack\_db\_database\_v1.mydb 7b9e3cd3-00d9-449c-b074-8439f8e274fa/mydb

# » openstack\_db\_user\_v1

Manages a V1 DB user resource within OpenStack.

## » Example Usage

#### » User

## » Argument Reference

The following arguments are supported:

- name (Required) A unique name for the resource.
- instance (Required) The ID for the database instance.
- password (Required) User's password.
- databases (Optional) A list of database user should have access to.

#### » Attributes Reference

The following attributes are exported:

- region Openstack region resource is created in.
  - name See Argument Reference above.
  - instance See Argument Reference above.
  - password See Argument Reference above.
- databases See Argument Reference above.

# » openstack\_db\_configuration\_v1

Manages a V1 DB configuration resource within OpenStack.

## » Example Usage

## » Configuration

```
datastore {
   version = "mysql-5.7"
   type = "mysql"
}

configuration {
   name = "max_connections"
   value = 200
}
```

## » Argument Reference

The following arguments are supported:

- region (Required) The region in which to create the db instance. Changing this creates a new instance.
- name (Required) A unique name for the resource.
- description (Optional) Description of the resource.
- datastore (Required) An array of database engine type and version.
   The datastore object structure is documented below. Changing this creates resource.
- configuration (Optional) An array of configuration parameter name and value. Can be specified multiple times. The configuration object structure is documented below.

The datastore block supports:

- type (Required) Database engine type to be used with this configuration. Changing this creates a new resource.
- version (Required) Version of database engine type to be used with this configuration. Changing this creates a new resource.

The configuration block supports:

- name (Optional) Configuration parameter name. Changing this creates a new resource.
- value (Optional) Configuration parameter value. Changing this creates a new resource.

## » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- datastore/type See Argument Reference above.
- datastore/version See Argument Reference above.
- configuration/name See Argument Reference above.
- configuration/value See Argument Reference above.

## » openstack\_dns\_recordset\_v2

Manages a DNS record set in the OpenStack DNS Service.

## » Example Usage

#### » Automatically detect the correct network

```
resource "openstack_dns_zone_v2" "example_zone" {
 name
              = "example.com."
              = "email2@example.com"
  email
  description = "a zone"
  ttl
              = 6000
              = "PRIMARY"
  type
}
resource "openstack dns recordset v2" "rs example com" {
 zone_id
              = "${openstack_dns_zone_v2.example_zone.id}"
              = "rs.example.com."
 name
 description = "An example record set"
              = 3000
 ttl
              = "A"
  type
              = ["10.0.0.1"]
 records
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 DNS client. If omitted, the region argument of the provider is used. Changing this creates a new DNS record set.
- zone\_id (Required) The ID of the zone in which to create the record set. Changing this creates a new DNS record set.

- name (Required) The name of the record set. Note the . at the end of the name. Changing this creates a new DNS record set.
- type (Optional) The type of record set. Examples: "A", "MX". Changing this creates a new DNS record set.
- ttl (Optional) The time to live (TTL) of the record set.
- description (Optional) A description of the record set.
- records (Optional) An array of DNS records. *Note:* if an IPv6 address contains brackets ([]), the brackets will be stripped and the modified address will be recorded in the state.
- value\_specs (Optional) Map of additional options. Changing this creates a new record set.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- type See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- records See Argument Reference above.
- zone\_id See Argument Reference above.
- value\_specs See Argument Reference above.

## » Import

This resource can be imported by specifying the zone ID and recordset ID, separated by a forward slash.

\$ terraform import openstack\_dns\_recordset\_v2.recordset\_1 <zone\_id>/<recordset\_id>

# » openstack\_dns\_zone\_v2

Manages a DNS zone in the OpenStack DNS Service.

## » Example Usage

## » Automatically detect the correct network

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new DNS zone.
- name (Required) The name of the zone. Note the . at the end of the name. Changing this creates a new DNS zone.
- email (Optional) The email contact for the zone record.
- type (Optional) The type of zone. Can either be PRIMARY or SECONDARY. Changing this creates a new zone.
- attributes (Optional) Attributes for the DNS Service scheduler. Changing this creates a new zone.
- ttl (Optional) The time to live (TTL) of the zone.
- description (Optional) A description of the zone.
- masters (Optional) An array of master DNS servers. For when type is SECONDARY.
- value\_specs (Optional) Map of additional options. Changing this creates a new zone.

#### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- email See Argument Reference above.

- type See Argument Reference above.
- attributes See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- masters See Argument Reference above.
- value\_specs See Argument Reference above.

## » Import

This resource can be imported by specifying the zone ID:

```
$ terraform import openstack_dns_zone_v2.zone_1 <zone_id>
```

# » openstack identity application credential v3

Manages a V3 Application Credential resource within OpenStack Keystone.

**Note:** All arguments including the application credential name and secret will be stored in the raw state as plain-text. Read more about sensitive data in state.

**Note:** An Application Credential is created within the authenticated user project scope and is not visible by an admin or other accounts. The Application Credential visibility is similar to openstack\_compute\_keypair\_v2.

## » Example Usage

## » Predefined secret

Application credential below will have only one swiftoperator role.

#### » Unrestricted with autogenerated secret and unlimited TTL

Application credential below will inherit all the current user's roles.

**WARNING:** Restrictions on these Identity operations are deliberately imposed as a safeguard to prevent a compromised application credential from regenerating itself. Disabling this restriction poses an inherent added risk.

#### » Application credential with access rules

**Note:** Application Credential access rules are supported only in Keystone starting from Train release.

#### » Argument Reference

- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new application credential.
- name (Required) A name of the application credential. Changing this creates a new application credential.

- description (Optional) A description of the application credential. Changing this creates a new application credential.
- unrestricted (Optional) A flag indicating whether the application credential may be used for creation or destruction of other application credentials or trusts. Changing this creates a new application credential.
- secret (Optional) The secret for the application credential. If omitted, it will be generated by the server. Changing this creates a new application credential.
- roles (Optional) A collection of one or more role names, which this application credential has to be associated with its project. If omitted, all the current user's roles within the scoped project will be inherited by a new application credential. Changing this creates a new application credential.
- access\_rules (Optional) A collection of one or more access rules, which this application credential allows to follow. The structure is described below. Changing this creates a new application credential.
- expires\_at (Optional) The expiration time of the application credential in the RFC3339 timestamp format (e.g. 2019-03-09T12:58:49Z). If omitted, an application credential will never expire. Changing this creates a new application credential.

## The access\_rules block supports:

- id (Computed) The ID of the existing access rule. The access rule ID of another application credential can be provided.
- path (Optional) The API path that the application credential is permitted to access. May use named wildcards such as {tag} or the unnamed wildcard \* to match against any string in the path up to a /, or the recursive wildcard \*\* to include / in the matched path.
- service (Optional) The service type identifier for the service that the application credential is granted to access. Must be a service type that is listed in the service catalog and not a code name for a service. E.g. identity, compute, volumev3, image, network, object-store, sharev2, dns, key-manager, monitoring, etc.
- method (Optional) The request method that the application credential is permitted to use for a given API endpoint. Allowed values: POST, GET, HEAD, PATCH, PUT and DELETE.

#### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- unrestricted See Argument Reference above.
- secret See Argument Reference above.
- roles See Argument Reference above.
- access\_rules See Argument Reference above.
- expires\_at See Argument Reference above.
- project\_id The ID of the project the application credential was created for and that authentication requests using this application credential will be scoped to.

#### » Import

Application Credentials can be imported using the id, e.g.

\$ terraform import openstack\_identity\_application\_credential\_v3.application\_credential\_1 c1

# » openstack\_identity\_endpoint\_v3

Manages a V3 Endpoint resource within OpenStack Keystone.

Note: This usually requires admin privileges.

#### » Example Usage

```
resource "openstack_identity_service_v3" "service_1" {
   name = "my-service"
   type = "my-service-type"
}

resource "openstack_identity_endpoint_v3" "endpoint_1" {
   name = "my-endpoint"
   service_id = "${openstack_identity_service_v3.service_1.id}"
   endpoint_region = "${openstack_identity_service_v3.service_1.region}"
   url = "http://my-endpoint"
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.
- name (Optional) The endpoint name.
- endpoint\_region (Required) The endpoint region. The region and endpoint\_region can be different.
- url (Required) The endpoint url.
- interface (Optional) The endpoint interface. Valid values are public, internal and admin. Default value is public
- service\_id (Required) The endpoint service ID.

#### » Attributes Reference

id is set to the ID of the endpoint. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- endpoint\_region See Argument Reference above.
- url See Argument Reference above.
- interface See Argument Reference above.
- service\_id See Argument Reference above.
- service\_name The service name of the endpoint.
- service\_type The service type of the endpoint.

## » Import

Endpoints can be imported using the id, e.g.

\$ terraform import openstack\_identity\_endpoint\_v3.endpoint\_1 5392472b-106a-4845-90c6-7c8445:

# ${\tt "openstack\_identity\_project\_v3"}$

Manages a V3 Project resource within OpenStack Keystone.

Note: You *must* have admin privileges in your OpenStack cloud to use this resource.

## » Example Usage

resource "openstack\_identity\_project\_v3" "project\_1" {

```
name = "project_1"
description = "A project"
}
```

## » Argument Reference

The following arguments are supported:

- description (Optional) A description of the project.
- domain\_id (Optional) The domain this project belongs to.
- enabled (Optional) Whether the project is enabled or disabled. Valid values are true and false.
- is\_domain (Optional) Whether this project is a domain. Valid values are true and false.
- name (Optional) The name of the project.
- parent\_id (Optional) The parent of this project.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new User.

#### » Attributes Reference

The following attributes are exported:

- domain\_id See Argument Reference above.
- parent\_id See Argument Reference above.

#### » Import

Projects can be imported using the id, e.g.

\$ terraform import openstack\_identity\_project\_v3.project\_1 89c60255-9bd6-460c-822a-e2b959ede

# ${\tt "openstack\_identity\_role\_v3"}$

Manages a V3 Role resource within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

## » Example Usage

```
resource "openstack_identity_role_v3" "role_1" {
  name = "role_1"
}
```

#### » Argument Reference

The following arguments are supported:

- name The name of the role.
- domain\_id (Optional) The domain the role belongs to.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new Role.

#### » Attributes Reference

The following attributes are exported:

- name See Argument Reference above.
- domain id See Argument Reference above.
- region See Argument Reference above.

#### » Import

Roles can be imported using the id, e.g.

```
$ terraform import openstack_identity_role_v3.role_1 89c60255-9bd6-460c-822a-e2b959ede9d2
```

# ${\tt "openstack\_identity\_role\_assignment\_v3}$

Manages a V3 Role assignment within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

#### » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
  name = "project_1"
```

#### » Argument Reference

The following arguments are supported:

- domain\_id (Optional; Required if project\_id is empty) The domain to assign the role in.
- group\_id (Optional; Required if user\_id is empty) The group to assign the role to.
- project\_id (Optional; Required if domain\_id is empty) The project to assign the role in.
- user\_id (Optional; Required if group\_id is empty) The user to assign
  the role to.
- role\_id (Required) The role to assign.

#### » Attributes Reference

- domain\_id See Argument Reference above.
- project\_id See Argument Reference above.
- group id See Argument Reference above.
- user\_id See Argument Reference above.
- role\_id See Argument Reference above.

# » openstack\_identity\_user\_v3

Manages a V3 User resource within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

## » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
 name = "project_1"
resource "openstack_identity_user_v3" "user_1" {
 default_project_id = "${openstack_identity_project_v3.project_1.id}"
 name
                     = "user 1"
                     = "A user"
 description
 password = "password123"
  ignore_change_password_upon_first_use = true
 multi_factor_auth_enabled = true
 multi_factor_auth_rule {
   rule = ["password", "totp"]
 multi_factor_auth_rule {
   rule = ["password"]
  extra = {
    email = "user_10foobar.com"
}
```

#### » Argument Reference

- description (Optional) A description of the user.
- default\_project\_id (Optional) The default project this user belongs

- domain\_id (Optional) The domain this user belongs to.
- enabled (Optional) Whether the user is enabled or disabled. Valid values are true and false.
- extra (Optional) Free-form key/value pairs of extra information.
- ignore\_change\_password\_upon\_first\_use (Optional) User will not have to change their password upon first use. Valid values are true and false.
- ignore\_password\_expiry (Optional) User's password will not expire. Valid values are true and false.
- ignore\_lockout\_failure\_attempts (Optional) User will not have a failure lockout placed on their account. Valid values are true and false.
- multi\_factor\_auth\_enabled (Optional) Whether to enable multifactor authentication. Valid values are true and false.
- multi\_factor\_auth\_rule (Optional) A multi-factor authentication rule. The structure is documented below. Please see the Ocata release notes for more information on how to use multi-factor rules.
- name (Optional) The name of the user.
- password (Optional) The password for the user.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new User.

The multi\_factor\_auth\_rule block supports:

• rule - (Required) A list of authentication plugins that the user must authenticate with.

#### » Attributes Reference

The following attributes are exported:

• domain\_id - See Argument Reference above.

#### » Import

Users can be imported using the id, e.g.

\$ terraform import openstack\_identity\_user\_v3.user\_1 89c60255-9bd6-460c-822a-e2b959ede9d2

# » openstack\_identity\_service\_v3

Manages a V3 Service resource within OpenStack Keystone.

Note: This usually requires admin privileges.

#### » Example Usage

```
resource "openstack_identity_service_v3" "service_1" {
  name = "custom"
  type = "custom"
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.
- name (Required) The service name.
- description (Optional) The service description.
- type (Required) The service type.
- enabled (Optional) The service status. Defaults to true.

#### » Attributes Reference

id is set to the ID of the found service. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- type See Argument Reference above.
- enabled See Argument Reference above.
- description See Argument Reference above.

#### » Import

Services can be imported using the id, e.g.

\$ terraform import openstack\_identity\_service\_v3.service\_1 6688e967-158a-496f-a224-cae3414e6

## » openstack\_images\_image\_v2

Manages a V2 Image resource within OpenStack Glance.

#### » Example Usage

#### » Argument Reference

- container\_format (Required) The container format. Must be one of "ami", "ari", "aki", "bare", "ovf".
- disk\_format (Required) The disk format. Must be one of "ami", "ari", "aki", "vhd", "vmdk", "raw", "qcow2", "vdi", "iso".
- local\_file\_path (Optional) This is the filepath of the raw image file that will be uploaded to Glance. Conflicts with image\_source\_url.
- image\_cache\_path (Optional) This is the directory where the images will be downloaded. Images will be stored with a filename corresponding to the url's md5 hash. Defaults to "\$HOME/.terraform/image\_cache"
- image\_source\_url (Optional) This is the url of the raw image that will be downloaded in the image\_cache\_path before being uploaded to Glance. Glance is able to download image from internet but the gophercloud library does not yet provide a way to do so. Conflicts with local\_file\_path.
- min\_disk\_gb (Optional) Amount of disk space (in GB) required to boot image. Defaults to 0.
- min\_ram\_mb (Optional) Amount of ram (in MB) required to boot image.
   Defauts to 0.
- name (Required) The name of the image.

- properties (Optional) A map of key/value pairs to set freeform information about an image. See the "Notes" section for further information about properties.
- protected (Optional) If true, image will not be deletable. Defaults to
- region (Optional) The region in which to obtain the V2 Glance client. A Glance client is needed to create an Image that can be used with a compute instance. If omitted, the region argument of the provider is used. Changing this creates a new Image.
- tags (Optional) The tags of the image. It must be a list of strings. At this time, it is not possible to delete all tags of an image.
- verify\_checksum (Optional) If false, the checksum will not be verified once the image is finished uploading. Defaults to true.
- visibility (Optional) The visibility of the image. Must be one of "public", "private", "community", or "shared". The ability to set the visibility depends upon the configuration of the OpenStack cloud.

#### » Attributes Reference

- checksum The checksum of the data associated with the image.
- container\_format See Argument Reference above.
- created\_at The date the image was created.
- disk format See Argument Reference above.
- file the trailing path after the glance endpoint that represent the location of the image or the path to retrieve it.
- id A unique ID assigned by Glance.
- metadata The metadata associated with the image. Image metadata allow for meaningfully define the image properties and tags. See https://docs.openstack.org/glance/latest/user/metadefs-concepts.html.
- min\_disk\_gb See Argument Reference above.
- min\_ram\_mb See Argument Reference above.
- name See Argument Reference above.
- owner The id of the openstack user who owns the image.
- properties See Argument Reference above.
- protected See Argument Reference above.
- region See Argument Reference above.
- schema The path to the JSON-schema that represent the image or image
- size\_bytes The size in bytes of the data associated with the image.
- status The status of the image. It can be "queued", "active" or "saving".
- tags See Argument Reference above.
- updated\_at The date the image was last updated.

- update\_at (Deprecated use updated\_at instead)
- visibility See Argument Reference above.

#### » Notes

#### » Properties

This resource supports the ability to add properties to a resource during creation as well as add, update, and delete properties during an update of this resource.

Newer versions of OpenStack are adding some read-only properties to each image. These properties start with the prefix os\_. If these properties are detected, this resource will automatically reconcile these with the user-provided properties.

In addition, the direct\_url property is also automatically reconciled if the Image Service set it.

#### » Import

Images can be imported using the id, e.g.

# » openstack\_images\_image\_access\_v2

Manages members for the shared OpenStack Glance V2 Image within the source project, which owns the Image.

#### » Example Usage

#### » Unprivileged user

Create a shared image and propose a membership to the bed6b6cbb86a4e2d8dc2735c2f1000e4 project ID.

```
properties = {
    key = "value"
}

resource "openstack_images_image_access_v2" "rancheros_member" {
    image_id = "${openstack_images_image_v2.rancheros.id}"
    member_id = "bed6b6cbb86a4e2d8dc2735c2f1000e4"
}
```

#### » Privileged user

Create a shared image and set a membership to the bed6b6cbb86a4e2d8dc2735c2f1000e4 project ID.

```
resource "openstack_images_image_v2" "rancheros" {
                  = "RancherOS"
  image_source_url = "https://releases.rancher.com/os/latest/rancheros-openstack.img"
  container_format = "bare"
 disk_format = "qcow2"
 visibility
                  = "shared"
 properties = {
   key = "value"
 }
}
resource "openstack_images_image_access_v2" "rancheros_member" {
  image_id = "${openstack_images_image_v2.rancheros.id}"
 member_id = "bed6b6cbb86a4e2d8dc2735c2f1000e4"
           = "accepted"
 status
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Glance client. A Glance client is needed to manage Image members. If omitted, the region argument of the provider is used. Changing this creates a new resource.
- image\_id (Required) The image ID.
- member\_id (Required) The member ID, e.g. the target project ID.
- status (Optional) The member proposal status. Optional if admin wants to force the member proposal acceptance. Can either be accepted,

rejected or pending. Defaults to pending. Foridden for non-admin users.

#### » Attributes Reference

The following attributes are exported:

- created\_at The date the image access was created.
- updated\_at The date the image access was last updated.
- schema The member schema.

### » Import

Image access can be imported using the image\_id and the member\_id, separated by a slash, e.g.

\$ terraform import openstack\_images\_image\_access\_v2 89c60255-9bd6-460c-822a-e2b959ede9d2/bed

# » openstack\_images\_image\_access\_accept\_v2

Manages memberships status for the shared OpenStack Glance V2 Image within the destination project, which has a member proposal.

## » Example Usage

Accept a shared image membershipship proposal within the current project.

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Glance client. A Glance client is needed to manage Image memberships. If omitted, the region argument of the provider is used. Changing this creates a new membership.
- image\_id (Required) The proposed image ID.
- member\_id (Optional) The member ID, e.g. the target project ID. Optional for admin accounts. Defaults to the current scope project ID.
- status (Required) The membership proposal status. Can either be accepted, rejected or pending.

#### » Attributes Reference

The following attributes are exported:

- created\_at The date the image membership was created.
- updated\_at The date the image membership was last updated.
- schema The membership schema.

## » Import

Image access acceptance status can be imported using the image\_id, e.g.

\$ terraform import openstack\_images\_image\_access\_accept\_v2 89c60255-9bd6-460c-822a-e2b959ede

# » openstack\_networking\_addressscope\_v2

Manages a V2 Neutron addressscope resource within OpenStack.

### » Example Usage

#### » Create an Address-scope

#### » Create a Subnet Pool from an Address-scope

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron address-scope. If omitted, the region argument of the provider is used. Changing this creates a new address-scope.
- name (Required) The name of the address-scope. Changing this updates the name of the existing address-scope.
- ip\_version (Optional) IP version, either 4 (default) or 6. Changing this creates a new address-scope.
- shared (Optional) Indicates whether this address-scope is shared across all projects. Changing this updates the shared status of the existing address-scope.
- project\_id (Optional) The owner of the address-scope. Required if admin wants to create a address-scope for another project. Changing this creates a new address-scope.

#### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- ip version See Argument Reference above.
- shared See Argument Reference above.
- project\_id See Argument Reference above.

#### » Import

Address-scopes can be imported using the id, e.g.

\$ terraform import openstack\_networking\_addressscope\_v2.addressscope\_1 9cc35860-522a-4d35-9

## » openstack\_networking\_floatingip\_v2

Manages a V2 floating IP resource within OpenStack Neutron (networking) that can be used for load balancers. These are similar to Nova (compute) floating IP resources, but only compute floating IPs can be used with compute instances.

#### » Example Usage

```
resource "openstack_networking_floatingip_v2" "floatip_1" {
  pool = "public"
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a floating IP that can be used with another networking resource, such as a load balancer. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- description (Optional) Human-readable description for the floating IP.
- pool (Required) The name of the pool from which to obtain the floating IP. Changing this creates a new floating IP.
- port\_id (Optional) ID of an existing port with at least one IP address to associate with this floating IP.
- tenant\_id (Optional) The target tenant ID in which to allocate the floating IP, if you specify this together with a port\_id, make sure the target port belongs to the same tenant. Changing this creates a new floating IP (which may or may not have a different address)
- address (Optional) The actual/specific floating IP to obtain. By default, non-admin users are not able to specify a floating IP, so you must either be an admin user or have had a custom policy or role applied to your OpenStack user or project.

- fixed\_ip Fixed IP of the port to associate with this floating IP. Required if the port has multiple fixed IPs.
- subnet\_id (Optional) The subnet ID of the floating IP pool. Specify this if the floating IP network has multiple subnets.
- value\_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the floating IP.
- dns\_name (Optional) The floating IP DNS name. Available, when Neutron DNS extension is enabled. The data in this attribute will be published in an external DNS service when Neutron is configured to integrate with such a service. Changing this creates a new floating IP.
- dns\_domain (Optional) The floating IP DNS domain. Available, when Neutron DNS extension is enabled. The data in this attribute will be published in an external DNS service when Neutron is configured to integrate with such a service. Changing this creates a new floating IP.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- description See Argument Reference above.
- pool See Argument Reference above.
- address The actual floating IP address itself.
- port\_id ID of associated port.
- tenant\_id the ID of the tenant in which to create the floating IP.
- fixed\_ip The fixed IP which the floating IP maps to.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the floating IP, which have been explicitly and implicitly added.
- dns\_name See Argument Reference above.
- dns\_domain See Argument Reference above.

#### » Import

Floating IPs can be imported using the id, e.g.

\$ terraform import openstack\_networking\_floatingip\_v2.floatip\_1 2c7f39f3-702b-48d1-940c-b503

# » openstack\_networking\_floatingip\_associate\_v2

Associates a floating IP to a port. This is useful for situations where you have a pre-allocated floating IP or are unable to use the openstack\_networking\_floatingip\_v2 resource to create a floating IP.

#### » Example Usage

```
resource "openstack_networking_port_v2" "port_1" {
   network_id = "a5bbd213-e1d3-49b6-aed1-9df60ea94b9a"
}
resource "openstack_networking_floatingip_associate_v2" "fip_1" {
   floating_ip = "1.2.3.4"
   port_id = "${openstack_networking_port_v2.port_1.id}"
}
```

#### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a floating IP that can be used with another networking resource, such as a load balancer. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- floating\_ip (Required) IP Address of an existing floating IP.
- port\_id (Required) ID of an existing port with at least one IP address to associate with this floating IP.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- floating\_ip See Argument Reference above.
- port\_id See Argument Reference above.

#### » Import

Floating IP associations can be imported using the id of the floating IP, e.g.

# » openstack\_networking\_network\_v2

Manages a V2 Neutron network resource within OpenStack.

#### » Example Usage

```
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
 admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
           = "subnet_1"
 network_id = "${openstack_networking_network_v2.network_1.id}"
         = "192.168.199.0/24"
 ip_version = 4
resource "openstack_compute_secgroup_v2" "secgroup_1" {
            = "secgroup_1"
 description = "a security group"
 rule {
   from_port = 22
   to_port = 22
   ip_protocol = "tcp"
              = "0.0.0.0/0"
   cidr
 }
}
resource "openstack_networking_port_v2" "port_1" {
                    = "port_1"
 name
 network id
                   = "${openstack_networking_network_v2.network_1.id}"
                  = "true"
 admin_state_up
 security_group_ids = ["${openstack_compute_secgroup_v2.secgroup_1.id}"]
 fixed_ip {
    "subnet_id" = "${openstack_networking_subnet_v2.subnet_1.id}"
    "ip_address" = "192.168.199.10"
 }
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron network. If omitted, the region argument of the provider is used. Changing this creates a new network.
- name (Optional) The name of the network. Changing this updates the name of the existing network.
- description (Optional) Human-readable description of the network. Changing this updates the name of the existing network.
- shared (Optional) Specifies whether the network resource can be accessed by any tenant or not. Changing this updates the sharing capabilities of the existing network.
- external (Optional) Specifies whether the network resource has the external routing facility. Valid values are true and false. Defaults to false. Changing this updates the external attribute of the existing network.
- tenant\_id (Optional) The owner of the network. Required if admin wants to create a network for another tenant. Changing this creates a new network.
- admin\_state\_up (Optional) The administrative state of the network. Acceptable values are "true" and "false". Changing this value updates the state of the existing network.
- segments (Optional) An array of one or more provider segment objects.
- value\_specs (Optional) Map of additional options.
- availability\_zone\_hints (Optional) An availability zone is used to make network resources highly available. Used for resources with high availability so that they are scheduled on different availability zones. Changing this creates a new network.

- tags (Optional) A set of string tags for the network.
- transparent\_vlan (Optional) Specifies whether the network resource has the VLAN transparent attribute set. Valid values are true and false. Defaults to false. Changing this updates the transparent\_vlan attribute of the existing network.
- port\_security\_enabled (Optional) Whether to explicitly enable or disable port security on the network. Port Security is usually enabled by default, so omitting this argument will usually result in a value of "true". Setting this explicitly to false will disable port security. Valid values are true and false.
- mtu (Optional) The network MTU. Available for read-only, when Neutron net-mtu extension is enabled. Available for the modification, when Neutron net-mtu-writable extension is enabled.
- dns\_domain (Optional) The network DNS domain. Available, when Neutron DNS extension is enabled. The dns\_domain of a network in conjunction with the dns\_name attribute of its ports will be published in an external DNS service when Neutron is configured to integrate with such a service.
- qos\_policy\_id (Optional) Reference to the associated QoS policy.

The segments block supports:

- physical\_network The physical network where this network is implemented.
- segmentation id An isolated segment on the physical network.
- network\_type The type of physical network.

#### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- shared See Argument Reference above.
- external See Argument Reference above.
- tenant\_id See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- availability\_zone\_hints See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the network, which have been explicitly and implicitly added.
- transparent vlan See Argument Reference above.
- port\_security\_enabled See Argument Reference above.

- mtu See Argument Reference above.
- dns\_domain See Argument Reference above.
- qos\_policy\_id See Argument Reference above.

#### » Import

Networks can be imported using the id, e.g.

\$ terraform import openstack\_networking\_network\_v2.network\_1 d90ce693-5ccf-4136-a0ed-152ce4

## » openstack\_networking\_port\_v2

Manages a V2 port resource within OpenStack.

## » Example Usage

## » Simple port

#### » Port with physical binding information

```
binding = {
              = "b080b9cf-46e0-4ce8-ad47-0fd4accc872b"
    vnic_type = "baremetal"
    profile
              = <<EOF
  "local_link_information": [
      "switch info": "info1",
      "port_id": "Ethernet3/4",
      "switch id": "12:34:56:78:9A:BC"
    },
      "switch info": "info2",
      "port id": "Ethernet3/4",
      "switch id": "12:34:56:78:9A:BD"
 ],
  "vlan_type": "allowed"
}
EOF
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new port.
- name (Optional) A unique name for the port. Changing this updates the name of an existing port.
- description (Optional) Human-readable description of the floating IP. Changing this updates the description of an existing port.
- network\_id (Required) The ID of the network to attach the port to. Changing this creates a new port.
- admin\_state\_up (Optional) Administrative up/down status for the port (must be "true" or "false" if provided). Changing this updates the admin\_state\_up of an existing port.
- mac\_address (Optional) Specify a specific MAC address for the port. Changing this creates a new port.

- tenant\_id (Optional) The owner of the Port. Required if admin wants to create a port for another tenant. Changing this creates a new port.
- device\_owner (Optional) The device owner of the Port. Changing this creates a new port.
- security\_group\_ids (Optional Conflicts with no\_security\_groups) A list of security group IDs to apply to the port. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).
- no\_security\_groups (Optional Conflicts with security\_group\_ids) If set to true, then no security groups are applied to the port. If set to false and no security\_group\_ids are specified, then the Port will yield to the default behavior of the Networking service, which is to usually apply the "default" security group.
- device\_id (Optional) The ID of the device attached to the port. Changing this creates a new port.
- fixed\_ip (Optional Conflicts with no\_fixed\_ip) An array of desired IPs for this port. The structure is described below.
- no\_fixed\_ip (Optional Conflicts with fixed\_ip) Create a port with no fixed IP address. This will also remove any fixed IPs previously set on a port. true is the only valid value for this argument.
- allowed\_address\_pairs (Optional) An IP/MAC Address pair of additional IP addresses that can be active on this port. The structure is described below.
- extra\_dhcp\_option (Optional) An extra DHCP option that needs to be configured on the port. The structure is described below. Can be specified multiple times.
- port\_security\_enabled (Optional) Whether to explicitly enable or disable port security on the port. Port Security is usually enabled by default, so omitting argument will usually result in a value of "true". Setting this explicitly to false will disable port security. In order to disable port security, the port must not have any security groups. Valid values are true and false.
- value\_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the port.
- binding (Optional) The port binding allows to specify binding information for the port. The structure is described below.
- dns\_name (Optional) The port DNS name. Available, when Neutron DNS extension is enabled.
- qos\_policy\_id (Optional) Reference to the associated QoS policy.

The fixed\_ip block supports:

- subnet\_id (Required) Subnet in which to allocate IP address for this port.
- ip\_address (Optional) IP address desired in the subnet for this port. If you don't specify ip\_address, an available IP address from the specified subnet will be allocated to this port. This field will not be populated if it is left blank or omitted. To retrieve the assigned IP address, use the all\_fixed\_ips attribute.

The allowed\_address\_pairs block supports:

- ip\_address (Required) The additional IP address.
- mac\_address (Optional) The additional MAC address.

The extra\_dhcp\_option block supports:

- name (Required) Name of the DHCP option.
- value (Required) Value of the DHCP option.
- ip\_version (Optional) IP protocol version. Defaults to 4.

The binding block supports:

- host\_id (Optional) The ID of the host to allocate port on.
- profile (Optional) Custom data to be passed as binding:profile. Data must be passed as JSON.
- vnic\_type (Optional) VNIC type for the port. Can either be direct, direct-physical, macvtap, normal, baremetal or virtio-forwarder. Default value is normal.
- vif\_details (Computed) A map of JSON strings containing additional details for this specific binding.
- vif\_type (Computed) The VNIC type of the port binding.

#### » Attributes Reference

- region See Argument Reference above.
- description See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- mac address See Argument Reference above.
- tenant\_id See Argument Reference above.
- device\_owner See Argument Reference above.
- security group ids See Argument Reference above.
- device\_id See Argument Reference above.

- fixed\_ip See Argument Reference above.
- all\_fixed\_ips The collection of Fixed IP addresses on the port in the order returned by the Network v2 API.
- all\_security\_group\_ids The collection of Security Group IDs on the port which have been explicitly and implicitly added.
- extra\_dhcp\_option See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the port, which have been explicitly and implicitly added.
- binding See Argument Reference above.
- dns\_name See Argument Reference above.
- dns\_assignment The list of maps representing port DNS assignments.
- qos\_policy\_id See Argument Reference above.

#### » Import

Ports can be imported using the id, e.g.

\$ terraform import openstack\_networking\_port\_v2.port\_1 eae26a3e-1c33-4cc1-9c31-0cd729c438a1

#### » Notes

#### » Ports and Instances

There are some notes to consider when connecting Instances to networks using Ports. Please see the openstack\_compute\_instance\_v2 documentation for further documentation.

# » openstack\_networking\_port\_secgroup\_associate\_v2

Manages a V2 port's security groups within OpenStack. Useful, when the port was created not by Terraform (e.g. Manila or LBaaS). It should not be used, when the port was created directly within Terraform.

When the resource is deleted, Terraform doesn't delete the port, but unsets the list of user defined security group IDs. However, if enforce is set to true and the resource is deleted, Terraform will remove all assigned security group IDs.

#### » Example Usage

#### » Append a security group to an existing port

data "openstack\_networking\_port\_v2" "system\_port" {

```
fixed_ip = "10.0.0.10"
data "openstack_networking_secgroup_v2" "secgroup" {
 name = "secgroup"
}
resource "openstack_networking_port_secgroup_associate_v2" "port_1" {
 port_id = "${data.openstack_networking_port_v2.system_port.id}"
  security_group_ids = [
    "${data.openstack_networking_secgroup_v2.secgroup.id}",
 ]
}
» Enforce a security group to an existing port
data "openstack_networking_port_v2" "system_port" {
 fixed_ip = "10.0.0.10"
}
data "openstack_networking_secgroup_v2" "secgroup" {
 name = "secgroup"
}
resource "openstack_networking_port_secgroup_associate_v2" "port_1" {
 port_id = "${data.openstack_networking_port_v2.system_port.id}"
  enforce = "true"
 security_group_ids = [
    "${data.openstack_networking_secgroup_v2.secgroup.id}",
 ٦
}
» Remove all security groups from an existing port
data "openstack_networking_port_v2" "system_port" {
  fixed_ip = "10.0.0.10"
}
resource "openstack_networking_port_secgroup_associate_v2" "port_1" {
                     = "${data.openstack_networking_port_v2.system_port.id}"
 port_id
                     = "true"
  enforce
 security_group_ids = []
}
```

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to manage a port. If omitted, the region argument of the provider is used. Changing this creates a new resource.
- port\_id (Required) An UUID of the port to apply security groups to.
- security\_group\_ids (Required) A list of security group IDs to apply to the port. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).
- enforce (Optional) Whether to replace or append the list of security groups, specified in the security\_group\_ids. Defaults to false.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- port\_id See Argument Reference above.
- security\_group\_ids See Argument Reference above.
- all\_security\_group\_ids The collection of Security Group IDs on the port which have been explicitly and implicitly added.

# » openstack\_networking\_qos\_bandwidth\_limit\_rule\_v2

Manages a V2 Neutron QoS bandwidth limit rule resource within OpenStack.

#### » Example Usage

» Create a QoS Policy with some bandwidth limit rule

```
direction = "egress"
}
```

#### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron QoS bandwidth limit rule. If omitted, the region argument of the provider is used. Changing this creates a new QoS bandwidth limit rule.
- qos\_policy\_id (Required) The QoS policy reference. Changing this creates a new QoS bandwidth limit rule.
- max\_kbps (Required) The maximum kilobits per second of a QoS bandwidth limit rule. Changing this updates the maximum kilobits per second of the existing QoS bandwidth limit rule.
- max\_burst\_kbps (Optional) The maximum burst size in kilobits of a QoS bandwidth limit rule. Changing this updates the maximum burst size in kilobits of the existing QoS bandwidth limit rule.
- direction (Optional) The direction of traffic. Defaults to "egress".
   Changing this updates the direction of the existing QoS bandwidth limit rule.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- qos\_policy\_id See Argument Reference above.
- max\_kbps See Argument Reference above.
- max\_burst\_kbps See Argument Reference above.
- direction See Argument Reference above.

#### » Import

QoS bandwidth limit rules can be imported using the qos\_policy\_id/bandwidth\_limit\_rule format, e.g.

\$ terraform import openstack\_networking\_qos\_bandwidth\_limit\_rule\_v2.bw\_limit\_rule\_1 d6ae28cc

# » openstack\_networking\_qos\_dscp\_marking\_rule\_v2

Manages a V2 Neutron QoS DSCP marking rule resource within OpenStack.

#### » Example Usage

#### » Create a QoS Policy with some DSCP marking rule

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron QoS DSCP marking rule. If omitted, the region argument of the provider is used. Changing this creates a new QoS DSCP marking rule.
- qos\_policy\_id (Required) The QoS policy reference. Changing this creates a new QoS DSCP marking rule.
- dscp\_mark (Required) The value of DSCP mark. Changing this updates the DSCP mark value existing QoS DSCP marking rule.

#### » Attributes Reference

- region See Argument Reference above.
- qos\_policy\_id See Argument Reference above.
- dscp\_mark See Argument Reference above.

### » Import

QoS DSCP marking rules can be imported using the qos\_policy\_id/dscp\_marking\_rule\_id format, e.g.

\$ terraform import openstack\_networking\_qos\_dscp\_marking\_rule\_v2.dscp\_marking\_rule\_1 d6ae28

# » openstack networking gos minimum bandwidth rule v2

Manages a V2 Neutron QoS minimum bandwidth rule resource within Open-Stack.

#### » Example Usage

» Create a QoS Policy with some minimum bandwidth rule

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron QoS minimum bandwidth rule. If omitted, the region argument of the provider is used. Changing this creates a new QoS minimum bandwidth rule.
- qos\_policy\_id (Required) The QoS policy reference. Changing this creates a new QoS minimum bandwidth rule.
- min\_kbps (Required) The minimum kilobits per second. Changing this updates the min kbps value of the existing QoS minimum bandwidth rule.
- direction (Optional) The direction of traffic. Defaults to "egress".
   Changing this updates the direction of the existing QoS minimum bandwidth rule.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- qos\_policy\_id See Argument Reference above.
- min\_kbps See Argument Reference above.
- direction See Argument Reference above.

#### » Import

QoS minimum bandwidth rules can be imported using the qos\_policy\_id/minimum\_bandwidth\_rule\_id format, e.g.

\$ terraform import openstack\_networking\_qos\_minimum\_bandwidth\_rule\_v2.minimum\_bandwidth\_rule

## » openstack networking gos policy v2

Manages a V2 Neutron QoS policy resource within OpenStack.

## » Example Usage

#### » Create a QoS Policy

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron Qos policy. If omitted, the region argument of the provider is used. Changing this creates a new QoS policy.
- name (Required) The name of the QoS policy. Changing this updates the name of the existing QoS policy.
- project\_id (Optional) The owner of the QoS policy. Required if admin wants to create a QoS policy for another project. Changing this creates a new QoS policy.

- shared (Optional) Indicates whether this QoS policy is shared across all projects. Changing this updates the shared status of the existing QoS policy.
- description (Optional) The human-readable description for the QoS policy. Changing this updates the description of the existing QoS policy.
- is\_default (Optional) Indicates whether the QoS policy is default QoS policy or not. Changing this updates the default status of the existing QoS policy.
- value\_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the QoS policy.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- project\_id See Argument Reference above.
- created\_at The time at which QoS policy was created.
- updated\_at The time at which QoS policy was created.
- shared See Argument Reference above.
- description See Argument Reference above.
- is\_default See Argument Reference above.
- revision\_number The revision number of the QoS policy.
- value\_specs See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the QoS policy, which have been explicitly and implicitly added.

#### » Import

QoS Policies can be imported using the id, e.g.

\$ terraform import openstack\_networking\_qos\_policy\_v2.qos\_policy\_1 d6ae28ce-fcb5-4180-aa62-c

# $ightsymbol{"}$ openstack\_networking\_quota\_v2

Manages a V2 networking quota resource within OpenStack.

Note: This usually requires admin privileges.

**Note:** This resource has a no-op deletion so no actual actions will be done against the OpenStack API in case of delete call.

#### » Example Usage

```
resource "openstack_identity_project_v2" "project_1" {
 name = project_1
}
resource "openstack_networking_quota_v2" "quota_1" {
 project_id
                      = "${openstack_identity_project_v2.project_1.id}"
                      = 10
 floatingip
 network
                      = 100
 port
                      = 10
 rbac_policy
 router
                      = 4
                      = 10
 security_group
  security_group_rule = 100
                      = 8
 subnet
                      = 2
  subnetpool
}
```

#### » Argument Reference

- region (Optional) The region in which to create the quota. If omitted, the region argument of the provider is used. Changing this creates new quota.
- project\_id (Required) ID of the project to manage quota. Changing this creates new quota.
- floatingip (Optional) Quota value for floating IPs. Changing this updates the existing quota.
- network (Optional) Quota value for networks. Changing this updates the existing quota.
- port (Optional) Quota value for ports. Changing this updates the existing quota.
- rbac\_policy (Optional) Quota value for RBAC policies. Changing this updates the existing quota.
- router (Optional) Quota value for routers. Changing this updates the existing quota.

- security\_group (Optional) Quota value for security groups. Changing this updates the existing quota.
- security\_group\_rule (Optional) Quota value for security group rules. Changing this updates the existing quota.
- subnet (Optional) Quota value for subnets. Changing this updates the existing quota.
- subnetpool (Optional) Quota value for subnetpools. Changing this updates the existing quota.

The following attributes are exported:

- region See Argument Reference above.
- project\_id See Argument Reference above.
- floatingip See Argument Reference above.
- network See Argument Reference above.
- port See Argument Reference above.
- rbac\_policy See Argument Reference above.
- router See Argument Reference above.
- security\_group See Argument Reference above.
- security\_group\_rule See Argument Reference above.
- subnet See Argument Reference above.
- subnetpool See Argument Reference above.

## » Import

Quotas can be imported using the project\_id, e.g.

\$ terraform import openstack\_networking\_quota\_v2.quota\_1 2a0f2240-c5e6-41de-896d-e80d97428de

# ${\tt "openstack\_networking\_router\_interface\_v2"}$

Manages a V2 router interface resource within OpenStack.

# » Example Usage

```
resource "openstack_networking_subnet_v2" "subnet_1" {
   network_id = "${openstack_networking_network_v2.network_1.id}"
   cidr = "192.168.199.0/24"
   ip_version = 4
}

resource "openstack_networking_router_v2" "router_1" {
   name = "my_router"
   external_network_id = "f67f0d72-0ddf-11e4-9d95-e1f29f417e2f"
}

resource "openstack_networking_router_interface_v2" "router_interface_1" {
   router_id = "${openstack_networking_router_v2.router_1.id}"
   subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
```

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a router. If omitted, the region argument of the provider is used. Changing this creates a new router interface.
- router\_id (Required) ID of the router this interface belongs to. Changing this creates a new router interface.
- subnet\_id ID of the subnet this interface connects to. Changing this creates a new router interface.
- port\_id ID of the port this interface connects to. Changing this creates a new router interface.

#### » Attributes Reference

- region See Argument Reference above.
- router\_id See Argument Reference above.
- subnet\_id See Argument Reference above.
- port\_id See Argument Reference above.

# » Import

Router Interfaces can be imported using the port id, e.g.

```
$ openstack port list --router <router name or id>
$ terraform import openstack_networking_router_interface_v2.int_1 <port id from above output</pre>
```

# » openstack networking router route v2

Creates a routing entry on a OpenStack V2 router.

# » Example Usage

```
resource "openstack_networking_router_v2" "router_1" {
 name
                = "router_1"
  admin_state_up = "true"
}
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
 network_id = "${openstack_networking_network_v2.network_1.id}"
           = "192.168.199.0/24"
  ip\_version = 4
resource "openstack_networking_router_interface_v2" "int_1" {
 router_id = "${openstack_networking_router_v2.router_1.id}"
  subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_networking_router_route_v2" "router_route_1" {
                  = ["openstack_networking_router_interface_v2.int_1"]
  depends_on
                  = "${openstack_networking_router_v2.router_1.id}"
 router_id
 destination_cidr = "10.0.1.0/24"
                 = "192.168.199.254"
 next_hop
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to configure a routing entry on a router. If omitted, the region argument of the provider is used. Changing this creates a new routing entry.
- router\_id (Required) ID of the router this routing entry belongs to.
   Changing this creates a new routing entry.
- destination\_cidr (Required) CIDR block to match on the packet's destination IP. Changing this creates a new routing entry.
- next\_hop (Required) IP address of the next hop gateway. Changing this creates a new routing entry.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- router id See Argument Reference above.
- destination\_cidr See Argument Reference above.
- next\_hop See Argument Reference above.

#### » Notes

The next\_hop IP address must be directly reachable from the router at the openstack\_networking\_router\_route\_v2 resource creation time. You can ensure that by explicitly specifying a dependency on the openstack\_networking\_router\_interface\_v2 resource that connects the next hop to the router, as in the example above.

## » Import

Routing entries can be imported using a combined ID using the following format: <router\_id>-route-<destination\_cidr>-<next\_hop>

\$ terraform import openstack\_networking\_router\_route\_v2.router\_route\_1 686fe248-386c-4f70-9

# » openstack\_networking\_router\_v2

Manages a V2 router resource within OpenStack.

# » Example Usage

# » Argument Reference

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a router. If omitted, the region argument of the provider is used. Changing this creates a new router.
- name (Optional) A unique name for the router. Changing this updates the name of an existing router.
- description (Optional) Human-readable description for the router.
- admin\_state\_up (Optional) Administrative up/down status for the router (must be "true" or "false" if provided). Changing this updates the admin\_state\_up of an existing router.
- distributed (Optional) Indicates whether or not to create a distributed router. The default policy setting in Neutron restricts usage of this property to administrative users only.
- external\_gateway (Deprecated use external\_network\_id instead)
  The network UUID of an external gateway for the router. A router with
  an external gateway is required if any compute instances or load balancers
  will be using floating IPs. Changing this updates the external gateway of
  an existing router.
- external\_network\_id (Optional) The network UUID of an external gateway for the router. A router with an external gateway is required if any compute instances or load balancers will be using floating IPs. Changing this updates the external gateway of the router.
- enable\_snat (Optional) Enable Source NAT for the router. Valid values are "true" or "false". An external\_network\_id has to be set in order to set this property. Changing this updates the enable\_snat of the router. Setting this value requires an ext-gw-mode extension to be enabled in OpenStack Neutron.
- external\_fixed\_ip (Optional) An external fixed IP for the router. This can be repeated. The structure is described below. An

- external\_network\_id has to be set in order to set this property. Changing this updates the external fixed IPs of the router.
- tenant\_id (Optional) The owner of the floating IP. Required if admin wants to create a router for another tenant. Changing this creates a new router.
- value\_specs (Optional) Map of additional driver-specific options.
- tags (Optional) A set of string tags for the router.
- vendor\_options (Optional) Map of additional vendor-specific options. Supported options are described below.
- availability\_zone\_hints (Optional) An availability zone is used to make network resources highly available. Used for resources with high availability so that they are scheduled on different availability zones. Changing this creates a new router.

The external\_fixed\_ip block supports:

- subnet\_id (Optional) Subnet in which the fixed IP belongs to.
- ip\_address (Optional) The IP address to set on the router.

The vendor\_options block supports:

• set\_router\_gateway\_after\_create - (Optional) Boolean to control whether the Router gateway is assigned during creation or updated after creation.

#### » Attributes Reference

- id ID of the router.
- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- external\_gateway See Argument Reference above.
- external\_network\_id See Argument Reference above.
- enable\_snat See Argument Reference above.
- external\_fixed\_ip See Argument Reference above.
- tenant\_id See Argument Reference above.
- value\_specs See Argument Reference above.
- availability\_zone\_hints See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the router, which have been
  explicitly and implicitly added.

## » Import

Routers can be imported using the id, e.g.

\$ terraform import openstack\_networking\_router\_v2.router\_1 014395cd-89fc-4c9b-96b7-13d1ee79c

# » openstack\_networking\_subnet\_v2

Manages a V2 Neutron subnet resource within OpenStack.

### » Example Usage

# » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron subnet. If omitted, the region argument of the provider is used. Changing this creates a new subnet.
- network\_id (Required) The UUID of the parent network. Changing this creates a new subnet.
- cidr (Optional) CIDR representing IP range for this subnet, based on IP version. You can omit this option if you are creating a subnet from a subnet pool.
- prefix\_length (Optional) The prefix length to use when creating a subnet from a subnet pool. The default subnet pool prefix length that was defined when creating the subnet pool will be used if not provided. Changing this creates a new subnet.
- ip\_version (Optional) IP version, either 4 (default) or 6. Changing this creates a new subnet.

- ipv6\_address\_mode (Optional) The IPv6 address mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- ipv6\_ra\_mode (Optional) The IPv6 Router Advertisement mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- name (Optional) The name of the subnet. Changing this updates the name of the existing subnet.
- description (Optional) Human-readable description of the subnet. Changing this updates the name of the existing subnet.
- tenant\_id (Optional) The owner of the subnet. Required if admin wants to create a subnet for another tenant. Changing this creates a new subnet.
- allocation\_pools (Deprecated use allocation\_pool instead) A block declaring the start and end range of the IP addresses available for use with DHCP in this subnet. The allocation\_pools block is documented below.
- allocation\_pool (Optional) A block declaring the start and end range of the IP addresses available for use with DHCP in this subnet. Multiple allocation\_pool blocks can be declared, providing the subnet with more than one range of IP addresses to use with DHCP. However, each IP range must be from the same CIDR that the subnet is part of. The allocation\_pool block is documented below.
- gateway\_ip (Optional) Default gateway used by devices in this subnet.
   Leaving this blank and not setting no\_gateway will cause a default gateway of .1 to be used. Changing this updates the gateway IP of the existing subnet.
- no\_gateway (Optional) Do not set a gateway IP on this subnet. Changing this removes or adds a default gateway IP of the existing subnet.
- enable\_dhcp (Optional) The administrative state of the network. Acceptable values are "true" and "false". Changing this value enables or disables the DHCP capabilities of the existing subnet. Defaults to true.
- dns\_nameservers (Optional) An array of DNS name server names used by hosts in this subnet. Changing this updates the DNS name servers for the existing subnet.
- host\_routes (Deprecated use openstack\_networking\_subnet\_route\_v2 instead) An array of routes that should be used by devices with IPs from this subnet (not including local subnet route). The host\_route object structure is documented below. Changing this updates the host routes for the existing subnet.
- subnetpool\_id (Optional) The ID of the subnetpool associated with the subnet.

- value\_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the subnet.

The deprecated allocation\_pools block supports:

- start (Required) The starting address.
- end (Required) The ending address.

The allocation\_pool block supports:

- start (Required) The starting address.
- end (Required) The ending address.

The host\_routes block supports:

- destination\_cidr (Required) The destination CIDR.
- next\_hop (Required) The next hop in the route.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- network\_id See Argument Reference above.
- cidr See Argument Reference above.
- ip\_version See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
  tenant id See Argument Reference above.
- allocation\_pools See Argument Reference above.
- gateway\_ip See Argument Reference above.
- enable\_dhcp See Argument Reference above.
- dns\_nameservers See Argument Reference above.
- host\_routes See Argument Reference above.
- subnetpool\_id See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of ags assigned on the subnet, which have been explicitly and implicitly added.

#### » Import

Subnets can be imported using the id, e.g.

\$ terraform import openstack\_networking\_subnet\_v2.subnet\_1 da4faf16-5546-41e4-8330-4d0002b74

# » openstack\_networking\_subnet\_route\_v2

Creates a routing entry on a OpenStack V2 subnet.

### » Example Usage

```
resource "openstack_networking_router_v2" "router_1" {
                = "router_1"
  admin_state_up = "true"
}
resource "openstack_networking_network_v2" "network_1" {
                = "network 1"
  admin_state_up = "true"
}
resource "openstack networking subnet v2" "subnet 1" {
 network_id = "${openstack_networking_network_v2.network_1.id}"
            = "192.168.199.0/24"
  ip\_version = 4
}
resource "openstack_networking_subnet_route_v2" "subnet_route_1" {
             = "${openstack_networking_subnet_v2.subnet_1.id}"
  {\tt subnet\_id}
  destination_cidr = "10.0.1.0/24"
                = "192.168.199.254"
 next_hop
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to configure a routing entry on a subnet. If omitted, the region argument of the provider is used. Changing this creates a new routing entry.
- subnet\_id (Required) ID of the subnet this routing entry belongs to. Changing this creates a new routing entry.
- destination\_cidr (Required) CIDR block to match on the packet's destination IP. Changing this creates a new routing entry.
- next\_hop (Required) IP address of the next hop gateway. Changing this
  creates a new routing entry.

The following attributes are exported:

- region See Argument Reference above.
- subnet\_id See Argument Reference above.
- destination\_cidr See Argument Reference above.
- next\_hop See Argument Reference above.

#### » Notes

#### » Import

Routing entries can be imported using a combined ID using the following format: <subnet\_id>-route-<destination\_cidr>-<next\_hop>

\$ terraform import openstack\_networking\_subnet\_route\_v2.subnet\_route\_1 686fe248-386c-4f70-99

# » openstack\_networking\_subnetpool\_v2

Manages a V2 Neutron subnetpool resource within OpenStack.

# » Example Usage

#### » Create a Subnet Pool

### » Create a Subnet from a Subnet Pool

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron subnetpool. If omitted, the region argument of the provider is used. Changing this creates a new subnetpool.
- name (Required) The name of the subnetpool. Changing this updates the name of the existing subnetpool.
- default\_quota (Optional) The per-project quota on the prefix space that can be allocated from the subnetpool for project subnets. Changing this updates the default quota of the existing subnetpool.
- project\_id (Optional) The owner of the subnetpool. Required if admin wants to create a subnetpool for another project. Changing this creates a new subnetpool.
- prefixes (Required) A list of subnet prefixes to assign to the subnetpool. Neutron API merges adjacent prefixes and treats them as a single prefix. Each subnet prefix must be unique among all subnet prefixes in all subnetpools that are associated with the address scope. Changing this updates the prefixes list of the existing subnetpool.
- default\_prefixlen (Optional) The size of the prefix to allocate when
  the cidr or prefixlen attributes are omitted when you create the subnet.
  Defaults to the MinPrefixLen. Changing this updates the default prefixlen
  of the existing subnetpool.
- min\_prefixlen (Optional) The smallest prefix that can be allocated from a subnetpool. For IPv4 subnetpools, default is 8. For IPv6 subnetpools, default is 64. Changing this updates the min prefixlen of the existing subnetpool.
- max\_prefixlen (Optional) The maximum prefix size that can be allocated from the subnetpool. For IPv4 subnetpools, default is 32. For IPv6 subnetpools, default is 128. Changing this updates the max prefixlen of the existing subnetpool.

- address\_scope\_id (Optional) The Neutron address scope to assign to the subnetpool. Changing this updates the address scope id of the existing subnetpool.
- shared (Optional) Indicates whether this subnetpool is shared across all projects. Changing this updates the shared status of the existing subnetpool.
- description (Optional) The human-readable description for the subnetpool. Changing this updates the description of the existing subnetpool.
- is\_default (Optional) Indicates whether the subnetpool is default subnetpool or not. Changing this updates the default status of the existing subnetpool.
- value\_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the subnetpool.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- default\_quota See Argument Reference above.
- project\_id See Argument Reference above.
- created\_at The time at which subnetpool was created.
- updated\_at The time at which subnetpool was created.
- prefixes See Argument Reference above.
- default prefixlen See Argument Reference above.
- min\_prefixlen See Argument Reference above.
- max\_prefixlen See Argument Reference above.
- address\_scope\_id See Argument Reference above.
- ip\_version The IP protocol version.
- shared See Argument Reference above.
- description See Argument Reference above.
- is\_default See Argument Reference above.
- revision\_number The revision number of the subnetpool.
- value\_specs See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the subnetpool, which have been explicitly and implicitly added.

#### » Import

Subnetpools can be imported using the id, e.g.

# » openstack\_networking\_secgroup\_v2

Manages a V2 neutron security group resource within OpenStack. Unlike Nova security groups, neutron separates the group from the rules and also allows an admin to target a specific tenant id.

### » Example Usage

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new security group.
- name (Required) A unique name for the security group.
- description (Optional) A unique name for the security group.
- tenant\_id (Optional) The owner of the security group. Required if admin wants to create a port for another tenant. Changing this creates a new security group.
- delete\_default\_rules (Optional) Whether or not to delete the default egress security rules. This is false by default. See the below note for more information.
- tags (Optional) A set of string tags for the security group.

#### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.

- tenant\_id See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the security group, which
  have been explicitly and implicitly added.

## » Default Security Group Rules

In most cases, OpenStack will create some egress security group rules for each new security group. These security group rules will not be managed by Terraform, so if you prefer to have *all* aspects of your infrastructure managed by Terraform, set delete\_default\_rules to true and then create separate security group rules such as the following:

Please note that this behavior may differ depending on the configuration of the OpenStack cloud. The above illustrates the current default Neutron behavior. Some OpenStack clouds might provide additional rules and some might not provide any rules at all (in which case the delete\_default\_rules setting is moot).

#### » Import

Security Groups can be imported using the id, e.g.

\$ terraform import openstack\_networking\_secgroup\_v2.secgroup\_1 38809219-5e8a-4852-9139-6f46

# » openstack\_networking\_secgroup\_rule\_v2

Manages a V2 neutron security group rule resource within OpenStack. Unlike Nova security groups, neutron separates the group from the rules and also allows an admin to target a specific tenant\_id.

# » Example Usage

```
resource "openstack_networking_secgroup_v2" "secgroup_1" {
             = "secgroup_1"
  description = "My neutron security group"
}
resource "openstack networking secgroup rule v2" "secgroup rule 1" {
  direction
                   = "ingress"
                   = "IPv4"
  ethertype
                  = "tcp"
 protocol
                   = 22
 port_range_min
                   = 22
 port_range_max
 remote_ip_prefix = "0.0.0.0/0"
  security_group_id = "${openstack_networking_secgroup_v2.secgroup_1.id}"
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new security group rule.
- description (Optional) A description of the rule. Changing this creates a new security group rule.
- direction (Required) The direction of the rule, valid values are **ingress** or **egress**. Changing this creates a new security group rule.
- ethertype (Required) The layer 3 protocol type, valid values are **IPv4** or **IPv6**. Changing this creates a new security group rule.
- protocol (Optional) The layer 4 protocol type, valid values are following. Changing this creates a new security group rule. This is required if you want to specify a port range.
  - tcp
     udp
     icmp
     ah
     dccp
     egp
     esp
     gre
     igmp

- ipv6-encap
- ipv6-frag
- ipv6-icmp
- ipv6-nonxt
- ipv6-opts
- ipv6-route
- ospf
- pgm
- rsvp
- sctp
- udplite
- vrrp
- port\_range\_min (Optional) The lower part of the allowed port range, valid integer value needs to be between 1 and 65535. Changing this creates a new security group rule.
- port\_range\_max (Optional) The higher part of the allowed port range, valid integer value needs to be between 1 and 65535. Changing this creates a new security group rule.
- remote\_ip\_prefix (Optional) The remote CIDR, the value needs to be a valid CIDR (i.e. 192.168.0.0/16). Changing this creates a new security group rule.
- remote\_group\_id (Optional) The remote group id, the value needs to be an Openstack ID of a security group in the same tenant. Changing this creates a new security group rule.
- security\_group\_id (Required) The security group id the rule should belong to, the value needs to be an Openstack ID of a security group in the same tenant. Changing this creates a new security group rule.
- tenant\_id (Optional) The owner of the security group. Required if admin wants to create a port for another tenant. Changing this creates a new security group rule.

- region See Argument Reference above.
- description See Argument Reference above.
- direction See Argument Reference above.
- ethertype See Argument Reference above.
- protocol See Argument Reference above.
- port range min See Argument Reference above.
- port range max See Argument Reference above.

- remote\_ip\_prefix See Argument Reference above.
- remote\_group\_id See Argument Reference above.
- security\_group\_id See Argument Reference above.
- tenant\_id See Argument Reference above.

### » Import

Security Group Rules can be imported using the id, e.g.

\$ terraform import openstack\_networking\_secgroup\_rule\_v2.secgroup\_rule\_1 aeb68ee3-6e9d-4256-

# » openstack\_networking\_trunk\_v2

Manages a networking V2 trunk resource within OpenStack.

# » Example Usage

```
resource "openstack_networking_network_v2" "network_1" {
                 = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
             = "subnet_1"
 network_id = "${openstack_networking_network_v2.network_1.id}"
             = "192.168.1.0/24"
 cidr
 ip\_version = 4
 enable_dhcp = true
 no_gateway = true
}
resource "openstack_networking_port_v2" "parent_port_1" {
  depends_on = [
    "openstack_networking_subnet_v2.subnet_1",
 ]
                 = "parent_port_1"
                = "${openstack_networking_network_v2.network_1.id}"
 network_id
  admin_state_up = "true"
}
resource "openstack_networking_port_v2" "subport_1" {
  depends_on = [
```

```
"openstack_networking_subnet_v2.subnet_1",
 ]
                 = "subport_1"
 name
 network_id
                 = "${openstack_networking_network_v2.network_1.id}"
  admin_state_up = "true"
}
resource "openstack_networking_trunk_v2" "trunk_1" {
                = "trunk 1"
  admin_state_up = "true"
                = "${openstack_networking_port_v2.parent_port_1.id}"
 port_id
  sub port {
   port_id
                      = "${openstack_networking_port_v2.subport_1.id}"
    segmentation id
    segmentation_type = "vlan"
 }
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance 1"
  security_groups = ["default"]
 network {
    port = "${openstack_networking_trunk_v2.trunk_1.port_id}"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a trunk. If omitted, the region argument of the provider is used. Changing this creates a new trunk.
- name (Optional) A unique name for the trunk. Changing this updates the name of an existing trunk.
- description (Optional) Human-readable description of the trunk. Changing this updates the name of the existing trunk.
- port\_id (Required) The ID of the port to be used as the parent port of the trunk. This is the port that should be used as the compute instance network port. Changing this creates a new trunk.

- admin\_state\_up (Optional) Administrative up/down status for the trunk (must be "true" or "false" if provided). Changing this updates the admin\_state\_up of an existing trunk.
- tenant\_id (Optional) The owner of the Trunk. Required if admin wants to create a trunk on behalf of another tenant. Changing this creates a new trunk.
- sub\_port (Optional) The set of ports that will be made subports of the trunk. The structure of each subport is described below.
- tags (Optional) A set of string tags for the port.

The sub\_port block supports:

- port\_id (Required) The ID of the port to be made a subport of the trunk.
- segmentation\_type (Required) The segmentation technology to use, e.g., "vlan".
- segmentation\_id (Required) The numeric id of the subport segment.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- port id See Argument Reference above.
- admin state up See Argument Reference above.
- tenant\_id See Argument Reference above.
- sub\_port See Argument Reference above.
- tags See Argument Reference above.
- all\_tags The collection of tags assigned on the trunk, which have been explicitly and implicitly added.

# ${\tt ~openstack\_networking\_rbac\_policy\_v2}$

The RBAC policy resource contains functionality for working with Neutron RBAC Policies. Role-Based Access Control (RBAC) policy framework enables both operators and users to grant access to resources for specific projects.

Sharing an object with a specific project is accomplished by creating a policy entry that permits the target project the access\_as\_shared action on that object.

To make a network available as an external network for specific projects rather than all projects, use the access\_as\_external action. If a network is marked as external during creation, it now implicitly creates a wildcard RBAC policy granting everyone access to preserve previous behavior before this feature was added.

# » Example Usage

# » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to configure a routing entry on a subnet. If omitted, the region argument of the provider is used. Changing this creates a new routing entry.
- action (Required) Action for the RBAC policy. Can either be access\_as\_external or access\_as\_shared.
- object\_id (Required) The ID of the object\_type resource. An object\_type of network returns a network ID and an object\_type of qos\_policy returns a QoS ID.
- object\_type (Required) The type of the object that the RBAC policy affects. Can either be qos-policy or network.
- target\_tenant (Required) The ID of the tenant to which the RBAC policy will be enforced.

#### » Attributes Reference

- region See Argument Reference above.
- action See Argument Reference above.
- object\_id See Argument Reference above.
- object\_type See Argument Reference above.
- target\_tenant See Argument Reference above.
- tenant\_id The owner of the RBAC policy.

#### » Notes

### » Import

RBAC policies can be imported using the id, e.g.

\$ terraform import openstack\_networking\_rbac\_policy\_v2.rbac\_policy\_1 eae26a3e-1c33-4cc1-9c3

# » openstack lb member v1

Manages a V1 load balancer member resource within OpenStack.

# » Example Usage

```
resource "openstack_lb_member_v1" "member_1" {
  pool_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"
  address = "192.168.0.10"
  port = 80
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB member. If omitted, the region argument of the provider is used. Changing this creates a new LB member.
- pool\_id (Required) The ID of the LB pool. Changing this creates a new member.
- address (Required) The IP address of the member. Changing this creates a new member.
- port (Required) An integer representing the port on which the member is hosted. Changing this creates a new member.

- admin\_state\_up (Optional) The administrative state of the member. Acceptable values are 'true' and 'false'. Changing this value updates the state of the existing member.
- tenant\_id (Optional) The owner of the member. Required if admin wants to create a member for another tenant. Changing this creates a new member.

The following attributes are exported:

- region See Argument Reference above.
- pool\_id See Argument Reference above.
- address See Argument Reference above.
- port See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- weight The load balancing weight of the member. This is currently unable to be set through Terraform.

## » Import

Load Balancer Members can be imported using the id, e.g.

```
$ terraform import openstack_lb_member_v1.member_1 a7498676-4fe4-4243-a864-2eaaf18c73df
```

# » openstack\_lb\_monitor\_v1

Manages a V1 load balancer monitor resource within OpenStack.

## » Example Usage

# » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB monitor. If omitted, the region argument of the provider is used. Changing this creates a new LB monitor.
- type (Required) The type of probe, which is PING, TCP, HTTP, or HTTPS, that is sent by the monitor to verify the member state. Changing this creates a new monitor.
- delay (Required) The time, in seconds, between sending probes to members. Changing this creates a new monitor.
- timeout (Required) Maximum number of seconds for a monitor to wait for a ping reply before it times out. The value must be less than the delay value. Changing this updates the timeout of the existing monitor.
- max\_retries (Required) Number of permissible ping failures before changing the member's status to INACTIVE. Must be a number between 1 and 10. Changing this updates the max retries of the existing monitor.
- url\_path (Optional) Required for HTTP(S) types. URI path that will be accessed if monitor type is HTTP or HTTPS. Changing this updates the url path of the existing monitor.
- http\_method (Optional) Required for HTTP(S) types. The HTTP method used for requests by the monitor. If this attribute is not specified, it defaults to "GET". Changing this updates the http\_method of the existing monitor.
- expected\_codes (Optional) Required for HTTP(S) types. Expected HTTP codes for a passing HTTP(S) monitor. You can either specify a single status like "200", or a range like "200-202". Changing this updates the expected\_codes of the existing monitor.
- admin\_state\_up (Optional) The administrative state of the monitor. Acceptable values are "true" and "false". Changing this value updates the state of the existing monitor.
- tenant\_id (Optional) The owner of the monitor. Required if admin
  wants to create a monitor for another tenant. Changing this creates a new
  monitor.

#### » Attributes Reference

- region See Argument Reference above.
- type See Argument Reference above.
- delay See Argument Reference above.
- timeout See Argument Reference above.
- max\_retries See Argument Reference above.
- url\_path See Argument Reference above.
- http\_method See Argument Reference above.
- expected\_codes See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- tenant\_id See Argument Reference above.

## » Import

Load Balancer Members can be imported using the id, e.g.

\$ terraform import openstack\_lb\_monitor\_v1.monitor\_1 119d7530-72e9-449a-aa97-124a5ef1992c

# » openstack\_lb\_pool\_v1

Manages a V1 load balancer pool resource within OpenStack.

### » Example Usage

#### » Complete Load Balancing Stack Example

```
ip\_version = 4
resource "openstack_compute_secgroup_v2" "secgroup_1" {
             = "secgroup_1"
 description = "Rules for secgroup_1"
 rule {
   from_port = -1
   to_port = -1
   ip_protocol = "icmp"
              = "0.0.0.0/0"
 }
 rule {
   from_port = 80
   to_port = 80
   ip_protocol = "tcp"
              = "0.0.0.0/0"
   cidr
 }
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
 security_groups = ["default", "${openstack_compute_secgroup_v2.secgroup_1.name}"]
 network {
   uuid = "${openstack_networking_network_v2.network_1.id}"
 }
}
resource "openstack_compute_instance_v2" "instance_2" {
                 = "instance_2"
 security_groups = ["default", "${openstack_compute_secgroup_v2.secgroup_1.name}"]
 network {
   uuid = "${openstack_networking_network_v2.network_1.id}"
 }
}
resource "openstack_lb_monitor_v1" "monitor_1" {
               = "TCP"
                = 30
 delay
                = 5
 timeout
 max_retries = 3
 admin_state_up = "true"
```

```
}
resource "openstack_lb_pool_v1" "pool_1" {
             = "pool_1"
 protocol
              = "TCP"
            = "${openstack_networking_subnet_v2.subnet_1.id}"
  subnet_id
             = "ROUND_ROBIN"
 lb_method
 monitor_ids = ["${openstack_lb_monitor_v1.monitor_1.id}"]
resource "openstack_lb_member_v1" "member_1" {
  pool_id = "${openstack_lb_pool_v1.pool_1.id}"
  address = "${openstack_compute_instance_v2.instance_1.access_ip_v4}"
}
resource "openstack_lb_member_v1" "member_2" {
 pool_id = "${openstack_lb_pool_v1.pool_1.id}"
 address = "${openstack_compute_instance_v2.instance_2.access_ip_v4}"
 port
}
resource "openstack_lb_vip_v1" "vip_1" {
            = "vip_1"
 name
  subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
 protocol = "TCP"
 port
            = "${openstack_lb_pool_v1.pool_1.id}"
 pool_id
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB pool. If omitted, the region argument of the provider is used. Changing this creates a new LB pool.
- name (Required) The name of the pool. Changing this updates the name of the existing pool.
- protocol (Required) The protocol used by the pool members, you can use either 'TCP, 'HTTP', or 'HTTPS'. Changing this creates a new pool.
- subnet\_id (Required) The network on which the members of the pool will be located. Only members that are on this network can be added to

the pool. Changing this creates a new pool.

- 1b\_method (Required) The algorithm used to distribute load between the members of the pool. The current specification supports 'ROUND ROBIN' and 'LEAST CONNECTIONS' as valid values for this attribute.
- 1b\_provider (Optional) The backend load balancing provider. For example: haproxy, F5, etc.
- tenant id (Optional) The owner of the pool. Required if admin wants to create a pool member for another tenant. Changing this creates a new pool.
- monitor\_ids (Optional) A list of IDs of monitors to associate with the
- member (Optional) An existing node to add to the pool. Changing this updates the members of the pool. The member object structure is documented below. Please note that the member block is deprecated in favor of the openstack\_lb\_member\_v1 resource.

#### The member block supports:

- address (Required) The IP address of the member. Changing this creates a new member.
- port (Required) An integer representing the port on which the member is hosted. Changing this creates a new member.
- admin state up (Required) The administrative state of the member. Acceptable values are 'true' and 'false'. Changing this value updates the state of the existing member.
- tenant\_id (Optional) The owner of the member. Required if admin wants to create a pool member for another tenant. Changing this creates a new member.

#### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- protocol See Argument Reference above.
- subnet\_id See Argument Reference above.
- 1b\_method See Argument Reference above. • lb\_provider - See Argument Reference above.
- tenant id See Argument Reference above.
- monitor id See Argument Reference above.

• member - See Argument Reference above.

#### » Notes

The member block is deprecated in favor of the openstack\_lb\_member\_v1 resource.

#### » Import

Load Balancer Pools can be imported using the id, e.g.

\$ terraform import openstack\_lb\_pool\_v1.pool\_1 b255e6ba-02ad-43e6-8951-3428ca26b713

# » openstack\_lb\_vip\_v1

Manages a V1 load balancer vip resource within OpenStack.

### » Example Usage

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VIP. If omitted, the region argument of the provider is used. Changing this creates a new VIP.
- name (Required) The name of the vip. Changing this updates the name of the existing vip.
- subnet\_id (Required) The network on which to allocate the vip's address. A tenant can only create vips on networks authorized by policy (e.g. networks that belong to them or networks that are shared). Changing this creates a new vip.

- protocol (Required) The protocol can be either 'TCP, 'HTTP', or HTTPS'. Changing this creates a new vip.
- port (Required) The port on which to listen for client traffic. Changing this creates a new vip.
- pool\_id (Required) The ID of the pool with which the vip is associated. Changing this updates the pool id of the existing vip.
- tenant\_id (Optional) The owner of the vip. Required if admin wants to create a vip member for another tenant. Changing this creates a new vip.
- address (Optional) The IP address of the vip. Changing this creates a new vip.
- description (Optional) Human-readable description for the vip. Changing this updates the description of the existing vip.
- persistence (Optional) Omit this field to prevent session persistence. The persistence object structure is documented below. Changing this updates the persistence of the existing vip.
- conn\_limit (Optional) The maximum number of connections allowed for the vip. Default is -1, meaning no limit. Changing this updates the conn\_limit of the existing vip.
- floating\_ip (Optional) A Networking Floating IP that will be associated with the vip. The Floating IP must be provisioned already.
- admin\_state\_up (Optional) The administrative state of the vip. Acceptable values are "true" and "false". Changing this value updates the state of the existing vip.

### The persistence block supports:

- type (Required) The type of persistence mode. Valid values are "SOURCE IP", "HTTP COOKIE", or "APP COOKIE".
- cookie\_name (Optional) The name of the cookie if persistence mode is set appropriately.

### » Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- subnet\_id See Argument Reference above.
- protocol See Argument Reference above.
- port See Argument Reference above.

- pool\_id See Argument Reference above.
- tenant\_id See Argument Reference above.
- address See Argument Reference above.
- description See Argument Reference above.
- persistence See Argument Reference above.
- conn\_limit See Argument Reference above.
- floating\_ip See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- port\_id Port UUID for this VIP at associated floating IP (if any).

# » Import

Load Balancer VIPs can be imported using the id, e.g.

\$ terraform import openstack\_lb\_vip\_v1.vip\_1 50e16b26-89c1-475e-a492-76167182511e

# » openstack\_lb\_loadbalancer\_v2

Manages a V2 loadbalancer resource within OpenStack.

# » Example Usage

```
resource "openstack_lb_loadbalancer_v2" "lb_1" {
   vip_subnet_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB member. If omitted, the region argument of the provider is used. Changing this creates a new LB member.
- vip\_subnet\_id (Required) The network on which to allocate the Load-balancer's address. A tenant can only create Loadbalancers on networks authorized by policy (e.g. networks that belong to them or networks that are shared). Changing this creates a new loadbalancer.
- name (Optional) Human-readable name for the Loadbalancer. Does not have to be unique.

- description (Optional) Human-readable description for the Loadbalancer.
- tenant\_id-(Optional) Required for admins. The UUID of the tenant who owns the Loadbalancer. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new loadbalancer.
- vip\_address (Optional) The ip address of the load balancer. Changing this creates a new loadbalancer.
- admin\_state\_up (Optional) The administrative state of the Loadbalancer. A valid value is true (UP) or false (DOWN).
- flavor\_id (Optional) The UUID of a flavor. Changing this creates a new loadbalancer.
- loadbalancer\_provider (Optional) The name of the provider. Changing this creates a new loadbalancer.
- security\_group\_ids (Optional) A list of security group IDs to apply to the loadbalancer. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).

The following attributes are exported:

- region See Argument Reference above.
- vip\_subnet\_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- tenant\_id See Argument Reference above.
- vip\_address See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- flavor\_id See Argument Reference above.
- loadbalancer\_provider See Argument Reference above.
- security\_group\_ids See Argument Reference above.
- vip\_port\_id The Port ID of the Load Balancer IP.

#### » Import

Load Balancer can be imported using the Load Balancer ID, e.g.:

\$ terraform import openstack\_lb\_loadbalancer\_v2.loadbalancer\_1 19bcfdc7-c521-4a7e-9459-67501

# » openstack\_lb\_listener\_v2

Manages a V2 listener resource within OpenStack.

### » Example Usage

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new Listener.
- protocol (Required) The protocol can either be TCP, HTTP, HTTPS, TERMINATED\_HTTPS or UDP (supported only in Octavia). Changing this creates a new Listener.
- protocol\_port (Required) The port on which to listen for client traffic. Changing this creates a new Listener.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the Listener. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new Listener.
- loadbalancer\_id (Required) The load balancer on which to provision this Listener. Changing this creates a new Listener.
- name (Optional) Human-readable name for the Listener. Does not have to be unique.
- default\_pool\_id (Optional) The ID of the default pool with which the Listener is associated.
- description (Optional) Human-readable description for the Listener.
- connection\_limit (Optional) The maximum number of connections allowed for the Listener.

- timeout\_client\_data (Optional) The client inactivity timeout in milliseconds.
- timeout\_member\_connect (Optional) The member connection timeout in milliseconds.
- timeout\_member\_data (Optional) The member inactivity timeout in milliseconds.
- timeout\_tcp\_inspect (Optional) The time in milliseconds, to wait for additional TCP packets for content inspection.
- default\_tls\_container\_ref (Optional) A reference to a Barbican Secrets container which stores TLS information. This is required if the protocol is TERMINATED\_HTTPS. See here for more information.
- sni\_container\_refs (Optional) A list of references to Barbican Secrets containers which store SNI information. See here for more information.
- admin\_state\_up (Optional) The administrative state of the Listener. A valid value is true (UP) or false (DOWN).
- insert\_headers (Optional) The list of key value pairs representing headers to insert into the request before it is sent to the backend members. Changing this updates the headers of the existing listener.

- id The unique ID for the Listener.
- protocol See Argument Reference above.
- protocol\_port See Argument Reference above.
- tenant id See Argument Reference above.
- name See Argument Reference above.
- default\_port\_id See Argument Reference above.
- description See Argument Reference above.
- connection\_limit See Argument Reference above.
- timeout\_client\_data See Argument Reference above.
- timeout\_member\_connect See Argument Reference above.
- timeout\_member\_data See Argument Reference above.
- timeout\_tcp\_inspect See Argument Reference above.
- default\_tls\_container\_ref See Argument Reference above.
- sni\_container\_refs See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- $\bullet\,$  insert\_headers See Argument Reference above.

### » Import

Load Balancer Listener can be imported using the Listener ID, e.g.:

\$ terraform import openstack\_lb\_listener\_v2.listener\_1 b67ce64e-8b26-405d-afeb-4a078901f15a

# » openstack\_lb\_pool\_v2

Manages a V2 pool resource within OpenStack.

### » Example Usage

```
resource "openstack_lb_pool_v2" "pool_1" {
  protocol = "HTTP"
  lb_method = "ROUND_ROBIN"
  listener_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"

  persistence {
    type = "APP_COOKIE"
    cookie_name = "testCookie"
  }
}
```

# » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new pool.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the pool. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new pool.
- name (Optional) Human-readable name for the pool.
- description (Optional) Human-readable description for the pool.
- protocol (Required) The protocol can either be TCP, HTTP, HTTPS, PROXY or UDP (supported only in Octavia). Changing this creates a new pool.
- loadbalancer\_id (Optional) The load balancer on which to provision this pool. Changing this creates a new pool. Note: One of LoadbalancerID or ListenerID must be provided.

- listener\_id (Optional) The Listener on which the members of the pool will be associated with. Changing this creates a new pool. Note: One of LoadbalancerID or ListenerID must be provided.
- 1b\_method (Required) The load balancing algorithm to distribute traffic to the pool's members. Must be one of ROUND\_ROBIN, LEAST CONNECTIONS, or SOURCE IP.
- persistence Omit this field to prevent session persistence. Indicates whether connections in the same session will be processed by the same Pool member or not. Changing this creates a new pool.
- admin\_state\_up (Optional) The administrative state of the pool. A valid value is true (UP) or false (DOWN).

The persistence argument supports:

- type (Required) The type of persistence mode. The current specification supports SOURCE\_IP, HTTP\_COOKIE, and APP\_COOKIE.
- cookie\_name (Optional) The name of the cookie if persistence mode is set appropriately. Required if type = APP\_COOKIE.

#### » Attributes Reference

The following attributes are exported:

- id The unique ID for the pool.
- tenant\_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- protocol See Argument Reference above.
- 1b method See Argument Reference above.
- persistence See Argument Reference above.
- admin\_state\_up See Argument Reference above.

### » Import

Load Balancer Pool can be imported using the Pool ID, e.g.:

\$ terraform import openstack\_lb\_pool\_v2.pool\_1 60ad9ee4-249a-4d60-a45b-aa60e046c513

# » openstack\_lb\_member\_v2

Manages a V2 member resource within OpenStack.

#### » Example Usage

```
resource "openstack_lb_member_v2" "member_1" {
  address = "192.168.199.23"
  protocol_port = 8080
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new member.
- pool\_id (Required) The id of the pool that this member will be assigned to.
- subnet\_id (Optional) The subnet in which to access the member
- name (Optional) Human-readable name for the member.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the member. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new member.
- address (Required) The IP address of the member to receive traffic from the load balancer. Changing this creates a new member.
- protocol\_port (Required) The port on which to listen for client traffic. Changing this creates a new member.
- weight (Optional) A positive integer value that indicates the relative portion of traffic that this member should receive from the pool. For example, a member with a weight of 10 receives five times as much traffic as a member with a weight of 2.
- admin\_state\_up (Optional) The administrative state of the member. A valid value is true (UP) or false (DOWN).

#### » Attributes Reference

The following attributes are exported:

- id The unique ID for the member.
- name See Argument Reference above.
- weight See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- tenant\_id See Argument Reference above.

- subnet\_id See Argument Reference above.
- pool\_id See Argument Reference above.
- address See Argument Reference above.
- protocol\_port See Argument Reference above.

#### » Import

Load Balancer Pool Member can be imported using the Pool ID and Member ID separated by a slash. e.g.:

\$ terraform import openstack\_lb\_member\_v2.member\_1 c22974d2-4c95-4bcb-9819-0afc5ed303d5/9563

# » openstack\_lb\_monitor\_v2

Manages a V2 monitor resource within OpenStack.

#### » Example Usage

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new monitor.
- pool\_id (Required) The id of the pool that this monitor will be assigned to.
- name (Optional) The Name of the Monitor.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the monitor. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new monitor.

- type (Required) The type of probe, which is PING, TCP, HTTP, HTTPS, TLS-HELLO or UDP-CONNECT (supported only in Octavia), that is sent by the load balancer to verify the member state. Changing this creates a new monitor.
- delay (Required) The time, in seconds, between sending probes to members.
- timeout (Required) Maximum number of seconds for a monitor to wait for a ping reply before it times out. The value must be less than the delay value.
- max\_retries (Required) Number of permissible ping failures before changing the member's status to INACTIVE. Must be a number between 1 and 10.
- max\_retries\_down (Optional) Number of permissible ping failures befor changing the member's status to ERROR. Must be a number between 1 and 10 (supported only in Octavia). Changing this updates the max\_retries\_down of the existing monitor.
- url\_path (Optional) Required for HTTP(S) types. URI path that will be accessed if monitor type is HTTP or HTTPS.
- http\_method (Optional) Required for HTTP(S) types. The HTTP method used for requests by the monitor. If this attribute is not specified, it defaults to "GET".
- expected\_codes (Optional) Required for HTTP(S) types. Expected HTTP codes for a passing HTTP(S) monitor. You can either specify a single status like "200", or a range like "200-202".
- admin\_state\_up (Optional) The administrative state of the monitor. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the monitor.
- tenant\_id See Argument Reference above.
- type See Argument Reference above.
- delay See Argument Reference above.
- timeout See Argument Reference above.
- max\_retries See Argument Reference above.
- max\_retries\_down See Argument Reference above.
- url\_path See Argument Reference above.
- http method See Argument Reference above.
- expected codes See Argument Reference above.

• admin\_state\_up - See Argument Reference above.

### » Import

Load Balancer Pool Monitor can be imported using the Monitor ID, e.g.:

```
$ terraform import openstack_lb_monitor_v2.monitor_1 47c26fc3-2403-427a-8c79-1589bd0533c2 In case of using OpenContrail, the import may not work properly. If you face an issue, try to import the monitor providing its parent pool ID:
```

\$ terraform import openstack\_lb\_monitor\_v2.monitor\_1 47c26fc3-2403-427a-8c79-1589bd0533c2/70

# » openstack\_lb\_l7policy\_v2

Manages a Load Balancer L7 Policy resource within OpenStack.

#### » Example Usage

```
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
            = "subnet_1"
            = "192.168.199.0/24"
 ip_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_lb_loadbalancer_v2" "loadbalancer_1" {
            = "loadbalancer 1"
  vip_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
resource "openstack_lb_listener_v2" "listener_1" {
                 = "listener_1"
 name
                 = "HTTP"
 protocol
 protocol_port = 8080
  loadbalancer_id = "${openstack_lb_loadbalancer_v2.loadbalancer_1.id}"
}
resource "openstack_lb_pool_v2" "pool_1" {
```

```
= "pool_1"
 name
                  = "HTTP"
 protocol
 1b method
                  = "ROUND ROBIN"
  loadbalancer_id = "${openstack_lb_loadbalancer_v2.loadbalancer_1.id}"
resource "openstack_lb_17policy_v2" "17policy_1" {
                  = "test"
 name
                   = "REDIRECT TO POOL"
  action
                 = "test 17 policy"
 description
 position
                  = 1
                  = "${openstack_lb_listener_v2.listener_1.id}"
 listener id
  redirect_pool_id = "${openstack_lb_pool_v2.pool_1.id}"
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new L7 Policy.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the L7 Policy. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new L7 Policy.
- name (Optional) Human-readable name for the L7 Policy. Does not have to be unique.
- description (Optional) Human-readable description for the L7 Policy.
- action (Required) The L7 Policy action can either be REDI-RECT\_TO\_POOL, REDIRECT\_TO\_URL or REJECT.
- listener\_id (Required) The Listener on which the L7 Policy will be associated with. Changing this creates a new L7 Policy.
- position (Optional) The position of this policy on the listener. Positions start at 1.
- redirect\_pool\_id (Optional) Requests matching this policy will be redirected to the pool with this ID. Only valid if action is REDI-RECT\_TO\_POOL.
- redirect\_url (Optional) Requests matching this policy will be redirected to this URL. Only valid if action is REDIRECT\_TO\_URL.
- admin\_state\_up (Optional) The administrative state of the L7 Policy. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the L7 Policy.
- region See Argument Reference above.
- tenant\_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- action See Argument Reference above.
- listener\_id See Argument Reference above.
- position See Argument Reference above.
- redirect\_pool\_id See Argument Reference above.
- redirect\_url See Argument Reference above.
- admin\_state\_up See Argument Reference above.

#### » Import

Load Balancer L7 Policy can be imported using the L7 Policy ID, e.g.:

 $\$\ terraform\ import\ openstack\_lb\_l7policy\_v2.l7policy\_1\ 8a7a79c2-cf17-4e65-b2ae-ddc8bfcf6c74-b2ae$ 

# » openstack\_lb\_l7rule\_v2

Manages a V2 L7 Rule resource within OpenStack.

#### » Example Usage

```
}
resource "openstack_lb_listener_v2" "listener_1" {
                  = "listener_1"
 protocol
                  = "HTTP"
                  = 8080
 protocol_port
  loadbalancer_id = "${openstack_lb_loadbalancer_v2.loadbalancer_1.id}"
}
resource "openstack_lb_pool_v2" "pool_1" {
                  = "pool_1"
                  = "HTTP"
 protocol
                 = "ROUND ROBIN"
 lb_method
  loadbalancer id = "${openstack lb loadbalancer v2.loadbalancer 1.id}"
}
resource "openstack_lb_17policy_v2" "17policy_1" {
               = "test"
               = "REDIRECT_TO_URL"
  action
 description = "test description"
 position
               = 1
 listener_id = "${openstack_lb_listener_v2.listener_1.id}"
  redirect_url = "http://www.example.com"
resource "openstack lb 17rule v2" "17rule 1" {
  17policy_id = "${openstack_lb_17policy_v2.17policy_1.id}"
              = "PATH"
  type
  compare_type = "EQUAL_TO"
               = "/api"
  value
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new L7 Rule.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the L7 Rule. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new L7 Rule.
- description (Optional) Human-readable description for the L7 Rule.

- type (Required) The L7 Rule type can either be COOKIE, FILE\_TYPE, HEADER, HOST\_NAME or PATH.
- compare\_type (Required) The comparison type for the L7 rule can either be CONTAINS, STARTS\_WITH, ENDS\_WITH, EQUAL\_TO or REGEX
- 17policy\_id (Required) The ID of the L7 Policy to query. Changing this creates a new L7 Rule.
- value (Required) The value to use for the comparison. For example, the file type to compare.
- key (Optional) The key to use for the comparison. For example, the name of the cookie to evaluate. Valid when type is set to COOKIE or HEADER.
- invert (Optional) When true the logic of the rule is inverted. For example, with invert true, equal to would become not equal to. Default is false
- admin\_state\_up (Optional) The administrative state of the L7 Rule. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the L7 Rule.
- region See Argument Reference above.
- tenant\_id See Argument Reference above.
- type See Argument Reference above.
- compare\_type See Argument Reference above.
- 17policy\_id See Argument Reference above.
- value See Argument Reference above.
- key See Argument Reference above.
- invert See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- listener\_id The ID of the Listener owning this resource.

#### » Import

Load Balancer L7 Rule can be imported using the L7 Policy ID and L7 Rule ID separated by a slash, e.g.:

\$ terraform import openstack\_lb\_17rule\_v2.17rule\_1 e0bd694a-abbe-450e-b329-0931fd1cc5eb/4086

# » openstack\_fw\_firewall\_v1

Manages a v1 firewall resource within OpenStack.

## » Example Usage

```
resource "openstack_fw_rule_v1" "rule_1" {
                 = "my-rule-1"
                 = "drop TELNET traffic"
 description
                 = "deny"
 action
 protocol = "tcp"
 destination_port = "23"
                 = "true"
  enabled
}
resource "openstack_fw_rule_v1" "rule_2" {
         = "my-rule-2"
 description = "drop NTP traffic"
petion = "don"
 action
                = "deny"
 protocol = "udp"
 destination_port = "123"
  enabled
            = "false"
}
resource "openstack_fw_policy_v1" "policy_1" {
 name = "my-policy"
 rules = ["${openstack_fw_rule_v1.rule_1.id}",
    "${openstack_fw_rule_v1.rule_2.id}",
 ]
}
resource "openstack_fw_firewall_v1" "firewall_1" {
           = "my-firewall"
 policy_id = "${openstack_fw_policy_v1.policy_1.id}"
```

#### » Argument Reference

The following arguments are supported:

• region - (Optional) The region in which to obtain the v1 networking client. A networking client is needed to create a firewall. If omitted, the region argument of the provider is used. Changing this creates a new firewall.

- policy\_id (Required) The policy resource id for the firewall. Changing this updates the policy\_id of an existing firewall.
- name (Optional) A name for the firewall. Changing this updates the name of an existing firewall.
- description (Required) A description for the firewall. Changing this updates the description of an existing firewall.
- admin\_state\_up (Optional) Administrative up/down status for the firewall (must be "true" or "false" if provided defaults to "true"). Changing this updates the admin\_state\_up of an existing firewall.
- tenant\_id (Optional) The owner of the floating IP. Required if admin
  wants to create a firewall for another tenant. Changing this creates a new
  firewall.
- associated\_routers (Optional) Router(s) to associate this firewall instance with. Must be a list of strings. Changing this updates the associated routers of an existing firewall. Conflicts with no\_routers.
- no\_routers (Optional) Should this firewall not be associated with any routers (must be "true" or "false" if provide defaults to "false"). Conflicts with associated\_routers.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- policy\_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- tenant\_id See Argument Reference above.
- associated\_routers See Argument Reference above.
- no\_routers See Argument Reference above.

#### » Import

Firewalls can be imported using the id, e.g.

\$ terraform import openstack\_fw\_firewall\_v1.firewall\_1 c9e39fb2-ce20-46c8-a964-25f3898c7a97

# » openstack\_fw\_policy\_v1

Manages a v1 firewall policy resource within OpenStack.

## » Example Usage

```
resource "openstack_fw_rule_v1" "rule_1" {
                = "my-rule-1"
                = "drop TELNET traffic"
 description
                = "deny"
 action
 protocol = "tcp"
 destination_port = "23"
                 = "true"
  enabled
}
resource "openstack_fw_rule_v1" "rule_2" {
         = "my-rule-2"
 description = "drop NTP traffic"
action = "deny"
 protocol = "udp"
 destination_port = "123"
  enabled
           = "false"
}
resource "openstack_fw_policy_v1" "policy_1" {
 name = "my-policy"
 rules = ["${openstack_fw_rule_v1.rule_1.id}",
    "${openstack_fw_rule_v1.rule_2.id}",
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the v1 networking client. A networking client is needed to create a firewall policy. If omitted, the region argument of the provider is used. Changing this creates a new firewall policy.
- name (Optional) A name for the firewall policy. Changing this updates the name of an existing firewall policy.

- description (Optional) A description for the firewall policy. Changing this updates the description of an existing firewall policy.
- rules (Optional) An array of one or more firewall rules that comprise the policy. Changing this results in adding/removing rules from the existing firewall policy.
- audited (Optional) Audit status of the firewall policy (must be "true" or "false" if provided defaults to "false"). This status is set to "false" whenever the firewall policy or any of its rules are changed. Changing this updates the audited status of an existing firewall policy.
- shared (Optional) Sharing status of the firewall policy (must be "true" or "false" if provided). If this is "true" the policy is visible to, and can be used in, firewalls in other tenants. Changing this updates the shared status of an existing firewall policy. Only administrative users can specify if the policy should be shared.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- audited See Argument Reference above.
- shared See Argument Reference above.

#### » Import

Firewall Policies can be imported using the id, e.g.

\$ terraform import openstack\_fw\_policy\_v1.policy\_1 07f422e6-c596-474b-8b94-fe2c12506ce0

# » openstack\_fw\_rule\_v1

Manages a v1 firewall rule resource within OpenStack.

#### » Example Usage

```
description = "drop TELNET traffic"
action = "deny"
protocol = "tcp"
destination_port = "23"
enabled = "true"
}
```

- region (Optional) The region in which to obtain the v1 Compute client. A Compute client is needed to create a firewall rule. If omitted, the region argument of the provider is used. Changing this creates a new firewall rule.
- name (Optional) A unique name for the firewall rule. Changing this updates the name of an existing firewall rule.
- description (Optional) A description for the firewall rule. Changing this updates the description of an existing firewall rule.
- protocol (Required) The protocol type on which the firewall rule operates. Valid values are: tcp, udp, icmp, and any. Changing this updates the protocol of an existing firewall rule.
- action (Required) Action to be taken (must be "allow" or "deny") when the firewall rule matches. Changing this updates the action of an existing firewall rule.
- ip\_version (Optional) IP version, either 4 (default) or 6. Changing this updates the ip version of an existing firewall rule.
- source\_ip\_address (Optional) The source IP address on which the firewall rule operates. Changing this updates the source\_ip\_address of an existing firewall rule.
- destination\_ip\_address (Optional) The destination IP address on which the firewall rule operates. Changing this updates the destination\_ip\_address of an existing firewall rule.
- source\_port (Optional) The source port on which the firewall rule operates. Changing this updates the source\_port of an existing firewall rule.
- destination\_port (Optional) The destination port on which the firewall rule operates. Changing this updates the destination\_port of an existing firewall rule.
- enabled (Optional) Enabled status for the firewall rule (must be "true" or "false" if provided defaults to "true"). Changing this updates the

enabled status of an existing firewall rule.

- tenant\_id (Optional) The owner of the firewall rule. Required if admin wants to create a firewall rule for another tenant. Changing this creates a new firewall rule.
- value\_specs (Optional) Map of additional options.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- protocol See Argument Reference above.
- action See Argument Reference above.
- ip\_version See Argument Reference above.
- source\_ip\_address See Argument Reference above.
- destination\_ip\_address See Argument Reference above.
- source\_port See Argument Reference above.
- destination\_port See Argument Reference above.
- enabled See Argument Reference above.
- tenant\_id See Argument Reference above.

#### » Import

Firewall Rules can be imported using the id, e.g.

```
$ terraform import openstack_fw_rule_v1.rule_1 8dbc0c28-e49c-463f-b712-5c5d1bbac327
```

# » openstack\_objectstorage\_container\_v1

Manages a V1 container resource within OpenStack.

#### » Example Usage

```
resource "openstack_objectstorage_container_v1" "container_1" {
  region = "RegionOne"
  name = "tf-test-container-1"

metadata = {
   test = "true"
```

```
}
content_type = "application/json"

versioning {
   type = "versions"
   location = "tf-test-container-versions"
}
```

The following arguments are supported:

- region (Optional) The region in which to create the container. If omitted, the region argument of the provider is used. Changing this creates a new container.
- name (Required) A unique name for the container. Changing this creates a new container.
- container\_read (Optional) Sets an access control list (ACL) that grants read access. This header can contain a comma-delimited list of users that can read the container (allows the GET method for all objects in the container). Changing this updates the access control list read access.
- container\_sync\_to (Optional) The destination for container synchronization. Changing this updates container synchronization.
- container\_sync\_key (Optional) The secret key for container synchronization. Changing this updates container synchronization.
- container\_write (Optional) Sets an ACL that grants write access. Changing this updates the access control list write access.
- versioning (Optional) Enable object versioning. The structure is described below.
- metadata (Optional) Custom key/value pairs to associate with the container. Changing this updates the existing container metadata.
- content\_type (Optional) The MIME type for the container. Changing this updates the MIME type.
- force\_destroy (Optional, Default:false) A boolean that indicates all objects should be deleted from the container so that the container can be destroyed without error. These objects are not recoverable.

The versioning block supports:

- type (Required) Versioning type which can be versions or history according to Openstack documentation.
- location (Required) Container in which versions will be stored.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- container\_read See Argument Reference above.
- container\_sync\_to See Argument Reference above.
- container\_sync\_key See Argument Reference above.
- container\_write See Argument Reference above.
- versioning See Argument Reference above.
- metadata See Argument Reference above.
- content\_type See Argument Reference above.

# » openstack\_objectstorage\_object\_v1

Manages a V1 container object resource within OpenStack.

#### » Example Usage

#### » Example with simple content

```
resource "openstack_objectstorage_container_v1" "container_1" {
    region = "RegionOne"
    name = "tf-test-container-1"

metadata {
    test = "true"
    }

    content_type = "application/json"
}

resource "openstack_objectstorage_object_v1" "doc_1" {
    region = "RegionOne"
    container_name = "${openstack_objectstorage_container_v1.container_1.name}"
    name = "test/default.json"
    metadata {
        test = "true"
```

```
}
  content_type = "application/json"
               = <<JSON
  content
                 "foo" : "bar"
JSON
}
» Example with content from file
resource "openstack_objectstorage_container_v1" "container_1" {
  region = "RegionOne"
         = "tf-test-container-1"
 name
 metadata {
    test = "true"
  content_type = "application/json"
}
resource "openstack_objectstorage_object_v1" "doc_1" {
                 = "RegionOne"
  container_name = "${openstack_objectstorage_container_v1.container_1.name}"
                 = "test/default.json"
 name
 metadata {
    test = "true"
 }
  content_type = "application/json"
  source
            = "./default.json"
}
```

The following arguments are supported:

• container\_name - (Required) A unique (within an account) name for the container. The container name must be from 1 to 256 characters long and can start with any character and contain any pattern. Character set must be UTF-8. The container name cannot contain a slash (/) character because this character delimits the container and object name. For example,

- the path /v1/account/www/pages specifies the www container, not the www/pages container.
- content (Optional) A string representing the content of the object. Conflicts with source and copy\_from.
- content\_disposition (Optional) A string which specifies the override behavior for the browser. For example, this header might specify that the browser use a download program to save this file rather than show the file, which is the default.
- content\_encoding (Optional) A string representing the value of the Content-Encoding metadata.
- content\_type (Optional) A string which sets the MIME type for the object.
- copy\_from (Optional) A string representing the name of an object used to create the new object by copying the copy\_from object. The value is in form {container}/{object}. You must UTF-8-encode and then URL-encode the names of the container and object before you include them in the header. Conflicts with source and content.
- delete\_after (Optional) An integer representing the number of seconds after which the system removes the object. Internally, the Object Storage system stores this value in the X-Delete-At metadata item.
- delete\_at (Optional) An string representing the date when the system removes the object. For example, "2015-08-26" is equivalent to Mon, Wed, 26 Aug 2015 00:00:00 GMT.
- detect\_content\_type (Optional) If set to true, Object Storage guesses
  the content type based on the file extension and ignores the value sent in
  the Content-Type header, if present.
- etag (Optional) Used to trigger updates. The only meaningful value is  ${\rm Md5(file("path/to/file"))}$ .
- name (Required) A unique name for the object.
- object\_manifest (Optional) A string set to specify that this is a dynamic large object manifest object. The value is the container and object name prefix of the segment objects in the form container/prefix. You must UTF-8-encode and then URL-encode the names of the container and prefix before you include them in this header.
- region (Optional) The region in which to create the container. If omitted, the region argument of the provider is used. Changing this creates a new container.
- source (Optional) A string representing the local path of a file which will be used as the object's content. Conflicts with source and copy\_from.

The following attributes are exported:

- content\_length If the operation succeeds, this value is zero (0) or the length of informational or error text in the response body.
- content\_type If the operation succeeds, this value is the MIME type of the object. If the operation fails, this value is the MIME type of the error text in the response body.
- date The date and time the system responded to the request, using the preferred format of RFC 7231 as shown in this example Thu, 16 Jun 2016 15:10:38 GMT. The time is always in UTC.
- etag Whatever the value given in argument, will be overriden by the MD5 checksum of the uploaded object content. The value is not quoted. If it is an SLO, it would be MD5 checksum of the segments' etags.
- last\_modified The date and time when the object was last modified. The date and time stamp format is ISO 8601: CCYY-MM-DDThh:mm:ss±hh:mm For example, 2015-08-27T09:49:58-05:00. The ±hh:mm value, if included, is the time zone as an offset from UTC. In the previous example, the offset value is -05:00.
- static\_large\_object True if object is a multipart\_manifest.
- trans\_id A unique transaction ID for this request. Your service provider might need this value if you report a problem.
- container\_name See Argument Reference above.
- content See Argument Reference above.
- content\_disposition See Argument Reference above.
- content\_encoding See Argument Reference above.
- copy\_from See Argument Reference above.
- delete\_after See Argument Reference above.
- delete\_at See Argument Reference above.
- detect\_content\_type See Argument Reference above.
- name See Argument Reference above.
- object\_manifest See Argument Reference above.
- region See Argument Reference above.
- source See Argument Reference above.

# » openstack\_objectstorage\_tempurl\_v1

Use this resource to generate an OpenStack Object Storage temporary URL.

The temporary URL will be valid for as long as TTL is set to (in seconds). Once the URL has expired, it will no longer be valid, but the resource will remain in place. If you wish to automatically regenerate a URL, set the regenerate argument to true. This will create a new resource with a new ID and URL.

#### » Example Usage

```
resource "openstack_objectstorage_tempurl_v1" "obj_tempurl" {
  container = "test"
  object = "container"
  method = "post"
  ttl = 20
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region the tempurl is located in.
- container (Required) The container name the object belongs to.
- object (Required) The object name the tempurl is for.
- ttl (Required) The TTL, in seconds, for the URL. For how long it should be valid.
- method (Optional) The method allowed when accessing this URL. Valid values are GET, and POST. Default is GET.
- regenerate (Optional) Whether to automatically regenerate the URL when it has expired. If set to true, this will create a new resource with a new ID and new URL. Defaults to false.

### » Attributes Reference

- id Computed md5 hash based on the generated url
- container See Argument Reference above.
- object See Argument Reference above.
- ttl See Argument Reference above.
- method See Argument Reference above.
- url The URL

• region - The region the endpoint is located in.

# » openstack\_vpnaas\_ipsec\_policy\_v2

Manages a V2 Neutron IPSec policy resource within OpenStack.

#### » Example Usage

```
resource "openstack_vpnaas_ipsec_policy_v2" "policy_1" {
  name = "my_policy"
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an IPSec policy. If omitted, the region argument of the provider is used. Changing this creates a new policy.
- name (Optional) The name of the policy. Changing this updates the name of the existing policy.
- tenant\_id (Optional) The owner of the policy. Required if admin wants to create a policy for another project. Changing this creates a new policy.
- description (Optional) The human-readable description for the policy. Changing this updates the description of the existing policy.
- auth\_algorithm (Optional) The authentication hash algorithm. Valid values are sha1, sha256, sha384, sha512. Default is sha1. Changing this updates the algorithm of the existing policy.
- encapsulation\_mode (Optional) The encapsulation mode. Valid values are tunnel and transport. Default is tunnel. Changing this updates the existing policy.
- encryption\_algorithm (Optional) The encryption algorithm. Valid values are 3des, aes-128, aes-192 and so on. The default value is aes-128. Changing this updates the existing policy.
- pfs (Optional) The perfect forward secrecy mode. Valid values are Group2, Group5 and Group14. Default is Group5. Changing this updates the existing policy.

- transform\_protocol (Optional) The transform protocol. Valid values are ESP, AH and AH-ESP. Changing this updates the existing policy. Default is ESP.
- lifetime (Optional) The lifetime of the security association. Consists
  of Unit and Value.
  - unit (Optional) The units for the lifetime of the security association.
     Can be either seconds or kilobytes. Default is seconds.
  - value (Optional) The value for the lifetime of the security association. Must be a positive integer. Default is 3600.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- description See Argument Reference above.
- auth\_algorithm See Argument Reference above.
- encapsulation\_mode See Argument Reference above.
- encryption\_algorithm See Argument Reference above.
- pfs See Argument Reference above.
- transform\_protocol See Argument Reference above.
- lifetime See Argument Reference above.
  - unit See Argument Reference above.
  - value See Argument Reference above.
- value\_specs See Argument Reference above.

#### » Import

Policies can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_ipsec\_policy\_v2.policy\_1 832cb7f3-59fe-40cf-8f64-8350ffc

# » openstack\_vpnaas\_ike\_policy\_v2

Manages a V2 Neutron IKE policy resource within OpenStack.

## » Example Usage

```
resource "openstack_vpnaas_ike_policy_v2" "policy_1" {
  name = "my_policy"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VPN service. If omitted, the region argument of the provider is used. Changing this creates a new service.
- name (Optional) The name of the policy. Changing this updates the name of the existing policy.
- tenant\_id (Optional) The owner of the policy. Required if admin wants to create a service for another policy. Changing this creates a new policy.
- description (Optional) The human-readable description for the policy. Changing this updates the description of the existing policy.
- auth\_algorithm (Optional) The authentication hash algorithm. Valid values are sha1, sha256, sha384, sha512. Default is sha1. Changing this updates the algorithm of the existing policy.
- encryption\_algorithm (Optional) The encryption algorithm. Valid values are 3des, aes-128, aes-192 and so on. The default value is aes-128. Changing this updates the existing policy.
- pfs (Optional) The perfect forward secrecy mode. Valid values are Group2, Group5 and Group14. Default is Group5. Changing this updates the existing policy.
- phase1\_negotiation\_mode (Optional) The IKE mode. A valid value is main, which is the default. Changing this updates the existing policy.
- ike\_version (Optional) The IKE mode. A valid value is v1 or v2. Default is v1. Changing this updates the existing policy.
- lifetime (Optional) The lifetime of the security association. Consists of Unit and Value.
  - unit (Optional) The units for the lifetime of the security association.
     Can be either seconds or kilobytes. Default is seconds.
  - value (Optional) The value for the lifetime of the security association. Must be a positive integer. Default is 3600.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- description See Argument Reference above.
- auth\_algorithm See Argument Reference above.
- encapsulation\_mode See Argument Reference above.
- encryption\_algorithm See Argument Reference above.
- pfs See Argument Reference above.
- transform\_protocol See Argument Reference above.
- lifetime See Argument Reference above.
  - unit See Argument Reference above.
  - value See Argument Reference above.
- value\_specs See Argument Reference above.

#### » Import

Services can be imported using the id, e.g.

# ${\tt "openstack\_vpnaas\_service\_v2"}$

Manages a V2 Neutron VPN service resource within OpenStack.

### » Example Usage

#### » Argument Reference

The following arguments are supported:

• region - (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VPN service. If omitted,

the **region** argument of the provider is used. Changing this creates a new service.

- name (Optional) The name of the service. Changing this updates the name of the existing service.
- tenant\_id (Optional) The owner of the service. Required if admin wants to create a service for another project. Changing this creates a new service.
- description (Optional) The human-readable description for the service. Changing this updates the description of the existing service.
- admin\_state\_up (Optional) The administrative state of the resource. Can either be up(true) or down(false). Changing this updates the administrative state of the existing service.
- subnet\_id (Optional) SubnetID is the ID of the subnet. Default is null.
- router\_id (Required) The ID of the router. Changing this creates a new service.
- value\_specs (Optional) Map of additional options.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- router id See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- subnet\_id See Argument Reference above.
- status Indicates whether IPsec VPN service is currently operational. Values are ACTIVE, DOWN, BUILD, ERROR, PENDING\_CREATE, PENDING\_UPDATE, or PENDING\_DELETE.
- external\_v6\_ip The read-only external (public) IPv6 address that is used for the VPN service.
- external\_v4\_ip The read-only external (public) IPv4 address that is used for the VPN service.
- description See Argument Reference above.
- value\_specs See Argument Reference above.

#### » Import

Services can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_service\_v2.service\_1 832cb7f3-59fe-40cf-8f64-8350ffc032

# » openstack\_vpnaas\_endpoint\_group\_v2

Manages a V2 Neutron Endpoint Group resource within OpenStack.

#### » Example Usage

```
resource "openstack_vpnaas_endpoint_group_v2" "group_1" {
  name = "Group 1"
  type = "cidr"
  endpoints = ["10.2.0.0/24",
  "10.3.0.0/24", ]
}
```

#### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an endpoint group. If omitted, the region argument of the provider is used. Changing this creates a new group.
- name (Optional) The name of the group. Changing this updates the name of the existing group.
- tenant\_id (Optional) The owner of the group. Required if admin wants to create an endpoint group for another project. Changing this creates a new group.
- description (Optional) The human-readable description for the group. Changing this updates the description of the existing group.
- type The type of the endpoints in the group. A valid value is subnet, cidr, network, router, or vlan. Changing this creates a new group.
- endpoints List of endpoints of the same type, for the endpoint group.

  The values will depend on the type. Changing this creates a new group.
- value\_specs (Optional) Map of additional options.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.

- description See Argument Reference above.
- type See Argument Reference above.
- endpoints See Argument Reference above.
- value\_specs See Argument Reference above.

## » Import

Groups can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_endpoint\_group\_v2.group\_1 832cb7f3-59fe-40cf-8f64-8350f

## » openstack\_vpnaas\_site\_connection\_v2

Manages a V2 Neutron IPSec site connection resource within OpenStack.

### » Example Usage

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an IPSec site connection. If omitted, the region argument of the provider is used. Changing this creates a new site connection.
- name (Optional) The name of the connection. Changing this updates the name of the existing connection.
- tenant\_id (Optional) The owner of the connection. Required if admin wants to create a connection for another project. Changing this creates a new connection.

- description (Optional) The human-readable description for the connection. Changing this updates the description of the existing connection.
- admin\_state\_up (Optional) The administrative state of the resource. Can either be up(true) or down(false). Changing this updates the administrative state of the existing connection.
- ikepolicy\_id (Required) The ID of the IKE policy. Changing this creates a new connection.
- vpnservice\_id (Required) The ID of the VPN service. Changing this
  creates a new connection.
- local\_ep\_group\_id (Optional) The ID for the endpoint group that contains private subnets for the local side of the connection. You must specify this parameter with the peer\_ep\_group\_id parameter unless in backward-compatible mode where peer\_cidrs is provided with a subnet\_id for the VPN service. Changing this updates the existing connection.
- ipsecpolicy\_id (Required) The ID of the IPsec policy. Changing this creates a new connection.
- peer\_id (Required) The peer router identity for authentication. A valid value is an IPv4 address, IPv6 address, e-mail address, key ID, or FQDN. Typically, this value matches the peer\_address value. Changing this updates the existing policy.
- peer\_ep\_group\_id (Optional) The ID for the endpoint group that contains private CIDRs in the form < net\_address > / < prefix > for the peer side of the connection. You must specify this parameter with the local\_ep\_group\_id parameter unless in backward-compatible mode where peer cidrs is provided with a subnet id for the VPN service.
- local\_id (Optional) An ID to be used instead of the external IP address for a virtual router used in traffic between instances on different networks in east-west traffic. Most often, local ID would be domain name, email address, etc. If this is not configured then the external IP address will be used as the ID.
- peer\_address (Required) The peer gateway public IPv4 or IPv6 address or FQDN.
- psk (Required) The pre-shared key. A valid value is any string.
- initiator (Optional) A valid value is response-only or bi-directional.
   Default is bi-directional.
- peer\_cidrs (Optional) Unique list of valid peer private CIDRs in the form < net\_address > / < prefix > .
- dpd (Optional) A dictionary with dead peer detection (DPD) protocol controls.

- action (Optional) The dead peer detection (DPD) action. A valid value is clear, hold, restart, disabled, or restart-by-peer. Default value is hold.
- timeout (Optional) The dead peer detection (DPD) timeout in seconds. A valid value is a positive integer that is greater than the DPD interval value. Default is 120.
- interval (Optional) The dead peer detection (DPD) interval, in seconds. A valid value is a positive integer. Default is 30.
- mtu (Optional) The maximum transmission unit (MTU) value to address fragmentation. Minimum value is 68 for IPv4, and 1280 for IPv6.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- description See Argument Reference above.
- dpd See Argument Reference above.
- psk See Argument Reference above.
- initiator See Argument Reference above.
- peer\_address See Argument Reference above.
- peer\_id See Argument Reference above.
- peer cidrs See Argument Reference above.
- mtu See Argument Reference above.
- local\_id See Argument Reference above.
- peer\_ep\_group\_id See Argument Reference above.
- ipsecpolicy\_id See Argument Reference above.
- vpnservice\_id See Argument Reference above.
- ikepolicy\_id See Argument Reference above.
- $\bullet\,$  value\_specs See Argument Reference above.

#### » Import

Site Connections can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_site\_connection\_v2.conn\_1 832cb7f3-59fe-40cf-8f64-8350f:

# » sharedfilesystem securityservice v2

Use this resource to configure a security service.

A security service stores configuration information for clients for authentication and authorization (AuthN/AuthZ). For example, a share server will be the client for an existing service such as LDAP, Kerberos, or Microsoft Active Directory.

Minimum supported Manila microversion is 2.7.

#### » Example Usage

```
resource "openstack_sharedfilesystem_securityservice_v2" "securityservice_1" {
              = "security"
  description = "created by terraform"
             = "active_directory"
  type
  server
              = "192.168.199.10"
              = "192.168.199.10"
  dns ip
              = "example.com"
  domain
              = "CN=Computers, DC=example, DC=com"
              = "joinDomainUser"
 user
              = "s8cret"
 password
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to create a security service. If omitted, the region argument of the provider is used. Changing this creates a new security service.
- name (Optional) The name of the security service. Changing this updates the name of the existing security service.
- description (Optional) The human-readable description for the security service. Changing this updates the description of the existing security service.
- type (Required) The security service type can either be active\_directory, kerberos or ldap. Changing this updates the existing security service.
- dns\_ip (Optional) The security service DNS IP address that is used inside the tenant network.

- ou (Optional) The security service ou. An organizational unit can be added to specify where the share ends up. New in Manila microversion 2.44.
- user (Optional) The security service user or group name that is used by the tenant.
- password (Optional) The user password, if you specify a user.
- domain (Optional) The security service domain.
- server (Optional) The security service host name or IP address.

- id The unique ID for the Security Service.
- region See Argument Reference above.
- project\_id The owner of the Security Service.
- name See Argument Reference above.
- description See Argument Reference above.
- type See Argument Reference above.
- dns\_ip See Argument Reference above.
- ou See Argument Reference above.
- user See Argument Reference above.
- password See Argument Reference above.
- domain See Argument Reference above.
- server See Argument Reference above.

#### » Import

This resource can be imported by specifying the ID of the security service:

\$ terraform import openstack\_sharedfilesystem\_securityservice\_v2.securityservice\_1 <id>

# ${\tt ~~shared filesystem\_share network\_v2}$

Use this resource to configure a share network.

A share network stores network information that share servers can use when shares are created.

## » Example Usage

#### » Basic share network

```
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
            = "subnet_1"
  cidr
            = "192.168.199.0/24"
 ip_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
                  = "test_sharenetwork"
 name
  description
                  = "test share network"
 neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
» Share network with associated security services
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
            = "subnet_1"
            = "192.168.199.0/24"
 cidr
 ip version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
resource "openstack_sharedfilesystem_securityservice_v2" "securityservice_1" {
             = "security"
 name
 description = "created by terraform"
          = "active_directory"
  server
            = "192.168.199.10"
            = "192.168.199.10"
  dns_ip
             = "example.com"
  domain
             = "CN=Computers, DC=example, DC=com"
  ou
```

```
user = "joinDomainUser"
password = "s8cret"
}

resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
   name = "test_sharenetwork"
   description = "test share network with security services"
   neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
   neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
   security_service_ids = [
    "${openstack_sharedfilesystem_securityservice_v2.securityservice_1.id}",
   ]
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to create a share network. If omitted, the region argument of the provider is used. Changing this creates a new share network.
- name (Optional) The name for the share network. Changing this updates the name of the existing share network.
- description (Optional) The human-readable description for the share network. Changing this updates the description of the existing share network.
- neutron\_net\_id (Required) The UUID of a neutron network when setting up or updating a share network. Changing this updates the existing share network if it's not used by shares.
- neutron\_subnet\_id (Required) The UUID of the neutron subnet when setting up or updating a share network. Changing this updates the existing share network if it's not used by shares.
- security\_service\_ids (Optional) The list of security service IDs to associate with the share network. The security service must be specified by ID and not name.

## » Attributes Reference

- id The unique ID for the Share Network.
- region See Argument Reference above.
- project\_id The owner of the Share Network.

- name See Argument Reference above.
- description See Argument Reference above.
- neutron\_net\_id See Argument Reference above.
- neutron\_subnet\_id See Argument Reference above.
- security\_service\_ids See Argument Reference above.
- network\_type The share network type. Can either be VLAN, VXLAN, GRE, or flat.
- segmentation\_id The share network segmentation ID.
- cidr The share network CIDR.
- ip\_version The IP version of the share network. Can either be 4 or 6.

#### » Import

This resource can be imported by specifying the ID of the share network:

\$ terraform import openstack\_sharedfilesystem\_sharenetwork\_v2.sharenetwork\_1 <id>

# » openstack\_sharedfilesystem\_share\_v2

Use this resource to configure a share.

#### » Example Usage

```
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
           = "subnet 1"
            = "192.168.199.0/24"
  cidr
 ip version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
                   = "test_sharenetwork"
 name
 description
                   = "test share network with security services"
 neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_sharedfilesystem_share_v2" "share_1" {
```

```
name = "nfs_share"
description = "test share description"
share_proto = "NFS"
size = 1
share_network_id = "${openstack_sharedfilesystem_sharenetwork_v2.sharenetwork_1.id}"
}
```

- region The region in which to obtain the V2 Shared File System client.
   A Shared File System client is needed to create a share. Changing this creates a new share.
- name (Optional) The name of the share. Changing this updates the name of the existing share.
- description (Optional) The human-readable description for the share. Changing this updates the description of the existing share.
- share\_proto (Required) The share protocol can either be NFS, CIFS, CEPHFS, GLUSTERFS, HDFS or MAPRFS. Changing this creates a new share
- size (Required) The share size, in GBs. The requested share size cannot be greater than the allowed GB quota. Changing this resizes the existing share
- share\_type (Optional) The share type name. If you omit this parameter, the default share type is used.
- snapshot\_id (Optional) The UUID of the share's base snapshot. Changing this creates a new share.
- is\_public (Optional) The level of visibility for the share. Set to true to make share public. Set to false to make it private. Default value is false. Changing this updates the existing share.
- metadata (Optional) One or more metadata key and value pairs as a dictionary of strings.
- share\_network\_id (Optional) The UUID of a share network where the share server exists or will be created. If share\_network\_id is not set and you provide a snapshot\_id, the share\_network\_id value from the snapshot is used. Changing this creates a new share.
- availability\_zone (Optional) The share availability zone. Changing this creates a new share.

- id The unique ID for the Share.
- region See Argument Reference above.
- project\_id The owner of the Share.
- name See Argument Reference above.
- description See Argument Reference above.
- share proto See Argument Reference above.
- size See Argument Reference above.
- share\_type See Argument Reference above.
- snapshot\_id See Argument Reference above.
- is\_public See Argument Reference above.
- metadata See Argument Reference above.
- share\_network\_id See Argument Reference above.
- availability\_zone See Argument Reference above.
- export\_locations A list of export locations. For example, when a share server has more than one network interface, it can have multiple export locations.
- has\_replicas Indicates whether a share has replicas or not.
- host The share host name.
- replication\_type The share replication type.
- share server id The UUID of the share server.
- all\_metadata The map of metadata, assigned on the share, which has been explicitly and implicitly added.

#### » Import

This resource can be imported by specifying the ID of the share:

\$ terraform import openstack\_sharedfilesystem\_share\_v2.share\_1 <id>

# $ightsymbol{"}$ openstack\_sharedfilesystem\_share\_access\_v2

Use this resource to control the share access lists.

**Important Security Notice** The access key retrieved by this resource will be stored *unencrypted* in your Terraform state file. If you use this resource in production, please make sure your state file is sufficiently protected.

# » Example Usage

#### » NFS

```
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
            = "subnet_1"
  cidr
            = "192.168.199.0/24"
 ip_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
                  = "test_sharenetwork"
  description
                  = "test share network with security services"
 neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_sharedfilesystem_share_v2" "share_1" {
                 = "nfs share"
                 = "test share description"
  description
  share_proto
                 = "NFS"
                  = 1
  share_network_id = "${openstack_sharedfilesystem_sharenetwork_v2.sharenetwork_1.id}"
}
resource "openstack_sharedfilesystem_share_access_v2" "share_access_1" {
             = "${openstack_sharedfilesystem_share_v2.share_1.id}"
  access_type = "ip"
              = "192.168.199.10"
  access_to
 access level = "rw"
}
» CIFS
resource "openstack_networking_network_v2" "network_1" {
                = "network 1"
  admin_state_up = "true"
```

```
resource "openstack_networking_subnet_v2" "subnet_1" {
            = "subnet_1"
            = "192.168.199.0/24"
 cidr
 ip_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_sharedfilesystem_securityservice_v2" "securityservice_1" {
             = "security"
 description = "created by terraform"
          = "active_directory"
 type
            = "192.168.199.10"
 server
           = "192.168.199.10"
 dns_ip
           = "example.com"
 domain
            = "CN=Computers, DC=example, DC=com"
 ou
            = "joinDomainUser"
 user
 password = "s8cret"
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
                   = "test_sharenetwork_secure"
                   = "share the secure love"
 description
 neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
 security_service_ids = [
    "${openstack_sharedfilesystem_securityservice_v2.securityservice_1.id}",
 ٦
}
resource "openstack_sharedfilesystem_share_v2" "share_1" {
                 = "cifs share"
                 = "CIFS"
 share_proto
                  = 1
 share_network_id = "${openstack_sharedfilesystem_sharenetwork_v2.sharenetwork_1.id}"
}
resource "openstack_sharedfilesystem_share_access_v2" "share_access_1" {
              = "${openstack_sharedfilesystem_share_v2.share_1.id}"
  share_id
 access_type = "user"
              = "windows"
 access_to
 access_level = "ro"
}
resource "openstack_sharedfilesystem_share_access_v2" "share_access_2" {
           = "${openstack_sharedfilesystem_share_v2.share_1.id}"
  access_type = "user"
```

```
access_to = "linux"
access_level = "rw"
}

output "export_locations" {
  value = "${openstack_sharedfilesystem_share_v2.share_1.export_locations}"
}
```

### » Argument Reference

The following arguments are supported:

- region The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to create a share access. Changing this creates a new share access.
- share\_id (Required) The UUID of the share to which you are granted access.
- access\_type (Required) The access rule type. Can either be an ip, user, cert, or cephx. cephx support requires an OpenStack environment that supports Shared Filesystem microversion 2.13 (Mitaka) or later.
- access\_to (Required) The value that defines the access. Can either be an IP address or a username verified by configured Security Service of the Share Network.
- access\_level (Required) The access level to the share. Can either be rw or ro.

# » Attributes Reference

- id The unique ID for the Share Access.
- region See Argument Reference above.
- share\_id See Argument Reference above.
- access\_type See Argument Reference above.
- access\_to See Argument Reference above.
- access\_level See Argument Reference above.
- access\_key The access credential of the entity granted access.

## » Import

This resource can be imported by specifying the ID of the share and the ID of the share access, separated by a slash, e.g.:

\$ terraform import openstack\_sharedfilesystem\_share\_access\_v2.share\_access\_1 <share id>/<share</pre>

# » openstack\_keymanager\_secret\_v1

Manages a V1 Barbican secret resource within OpenStack.

Important Security Notice The payload of this resource will be stored *unencrypted* in your Terraform state file. Use of this resource for production deployments is *not* recommended.

# » Example Usage

### » Simple secret

```
resource "openstack_keymanager_secret_v1" "secret_1" {
  algorithm
                      = "aes"
                      = 256
 bit_length
                      = "cbc"
 mode
                      = "mysecret"
 name
                      = "foobar"
 payload
 payload_content_type = "text/plain"
                      = "passphrase"
 secret_type
 metadata = {
   key = "foo"
}
```

#### » Secret with whitespaces

## » Secret with the expiration date

```
expiration
                       = "${timeadd(timestamp(), format("%dh", 8760))}" # one year in hours
 lifecycle {
    ignore_changes = [
      expiration
   ]
 }
}
» Secret with the ACL
Note Only read ACLs are supported
resource "openstack_keymanager_secret_v1" "secret_1" {
 name
                       = "certificate"
                       = "${file("certificate.pem")}"
 payload
                       = "certificate"
 secret_type
 payload_content_type = "text/plain"
 acl {
   read {
      project_access = false
      users = [
        "userid1",
        "userid2",
```

### » Argument Reference

} } }

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 KeyManager client. A KeyManager client is needed to create a secret. If omitted, the region argument of the provider is used. Changing this creates a new V1 secret.
- name (Optional) Human-readable name for the Secret. Does not have to be unique.
- bit\_length (Optional) Metadata provided by a user or system for informational purposes.
- algorithm (Optional) Metadata provided by a user or system for informational purposes.

- mode (Optional) Metadata provided by a user or system for informational purposes.
- secret\_type (Optional) Used to indicate the type of secret being stored. For more information see Secret types.
- payload (Optional) The secret's data to be stored. payload\_content\_type must also be supplied if payload is included.
- payload\_content\_type (Optional) (required if **payload** is included) The media type for the content of the payload. Must be one of text/plain, text/plain; charset=utf-8, text/plain; charset=utf-8, application/octet-stream, application/pkcs8.
- payload\_content\_encoding (Optional) (required if payload is encoded) The encoding used for the payload to be able to include it in the JSON request. Must be either base64 or binary.
- expiration (Optional) The expiration time of the secret in the RFC3339 timestamp format (e.g. 2019-03-09T12:58:49Z). If omitted, a secret will never expire. Changing this creates a new secret.
- metadata (Optional) Additional Metadata for the secret.
- acl (Optional) Allows to control an access to a secret. Currently only
  the read operation is supported. If not specified, the secret is accessible
  project wide.

The acl read block supports:

- project\_access (Optional) Whether the secret is accessible project wide.
   Defaults to true.
- users (Optional) The list of user IDs, which are allowed to access the secret, when project\_access is set to false.
- created\_at (Computed) The date the secret ACL was created.
- updated at (Computed) The date the secret ACL was last updated.

### » Attributes Reference

The following attributes are exported:

- secret\_ref The secret reference / where to find the secret.
- region See Argument Reference above.
- name See Argument Reference above.
- bit length See Argument Reference above.
- algorithm See Argument Reference above.
- mode See Argument Reference above.
- secret type See Argument Reference above.

- payload See Argument Reference above.
- payload\_content\_type See Argument Reference above.
- acl See Argument Reference above.
- payload\_content\_encoding See Argument Reference above.
- expiration See Argument Reference above.
- content\_types The map of the content types, assigned on the secret.
- creator\_id The creator of the secret.
- status The status of the secret.
- created\_at The date the secret was created.
- updated\_at The date the secret was last updated.
- all\_metadata The map of metadata, assigned on the secret, which has been explicitly and implicitly added.

### » Import

Secrets can be imported using the secret id (the last part of the secret reference), e.g.:

\$ terraform import openstack\_keymanager\_secret\_v1.secret\_1 8a7a79c2-cf17-4e65-b2ae-ddc8bfcf6

# » openstack\_keymanager\_container\_v1

Manages a V1 Barbican container resource within OpenStack.

### » Example Usage

#### » Simple secret

The container with the TLS certificates, which can be used by the loadbalancer HTTPS listener.

```
resource "openstack_keymanager_secret_v1" "certificate_1" {
                     = "certificate"
 name
 payload
                      = "${file("cert.pem")}"
 secret_type
                      = "certificate"
 payload_content_type = "text/plain"
resource "openstack_keymanager_secret_v1" "private_key_1" {
                     = "private_key"
 name
                      = "${file("cert-key.pem")}"
 payload
 secret_type
                     = "private"
 payload_content_type = "text/plain"
```

```
}
resource "openstack_keymanager_secret_v1" "intermediate_1" {
                      = "intermediate"
  payload
                      = "${file("intermediate-ca.pem")}"
                      = "certificate"
  secret_type
  payload_content_type = "text/plain"
}
resource "openstack_keymanager_container_v1" "tls_1" {
  name = "tls"
  type = "certificate"
  secret refs {
          = "certificate"
    secret_ref = "${openstack_keymanager_secret_v1.certificate_1.secret_ref}"
  secret_refs {
             = "private_key"
    secret_ref = "${openstack_keymanager_secret_v1.private_key_1.secret_ref}"
  secret_refs {
    name = "intermediates"
    secret_ref = "${openstack_keymanager_secret_v1.intermediate_1.secret_ref}"
  }
}
data "openstack_networking_subnet_v2" "subnet_1" {
  name = "my-subnet"
resource "openstack_lb_loadbalancer_v2" "lb_1" {
              = "loadbalancer"
  vip_subnet_id = "${data.openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_lb_listener_v2" "listener_1" {
                           = "https"
                           = "TERMINATED_HTTPS"
 protocol
  protocol_port
                           = 443
                           = "${openstack_lb_loadbalancer_v2.lb_1.id}"
  loadbalancer_id
  default_tls_container_ref = "${openstack_keymanager_container_v1.tls_1.container_ref}"
}
```

### » Container with the ACL

Note Only read ACLs are supported

```
resource "openstack_keymanager_container_v1" "tls_1" {
 name = "tls"
 type = "certificate"
 secret_refs {
           = "certificate"
   name
    secret_ref = "${openstack_keymanager_secret_v1.certificate_1.secret_ref}"
 }
 secret_refs {
              = "private_key"
   name
    secret_ref = "${openstack_keymanager_secret_v1.private_key_1.secret_ref}"
 secret_refs {
             = "intermediates"
   name
    secret_ref = "${openstack_keymanager_secret_v1.intermediate_1.secret_ref}"
 acl {
   read {
     project_access = false
     users = [
        "userid1",
        "userid2",
     ]
   }
 }
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 KeyManager client. A KeyManager client is needed to create a container. If omitted, the region argument of the provider is used. Changing this creates a new V1 container.
- name (Optional) Human-readable name for the Container. Does not have to be unique.

- type (Required) Used to indicate the type of container. Must be one of generic, rsa or certificate.
- secret\_refs (Optional) A set of dictionaries containing references to secrets. The structure is described below.
- acl (Optional) Allows to control an access to a container. Currently only the read operation is supported. If not specified, the container is accessible project wide. The read structure is described below.

### The secret\_refs block supports:

- name (Optional) The name of the secret reference. The reference names must correspond the container type, more details are available here.
- secret\_ref (Required) The secret reference / where to find the secret,
   URL.

# The acl read block supports:

- project\_access (Optional) Whether the container is accessible project wide. Defaults to true.
- users (Optional) The list of user IDs, which are allowed to access the container, when project\_access is set to false.
- created\_at (Computed) The date the container ACL was created.
- updated\_at (Computed) The date the container ACL was last updated.

### » Attributes Reference

The following attributes are exported:

- container ref The container reference / where to find the container.
- region See Argument Reference above.
- name See Argument Reference above.
- type See Argument Reference above.
- secret\_refs See Argument Reference above.
- acl See Argument Reference above.
- $\bullet$   ${\tt creator\_id}$  The creator of the container.
- status The status of the container.
- created\_at The date the container was created.
- updated\_at The date the container was last updated.
- consumers The list of the container consumers. The structure is described below.

### The consumers block supports:

- name The name of the consumer.
- url The consumer URL.

## » Import

Containers can be imported using the container id (the last part of the container reference), e.g.:

\$ terraform import openstack\_keymanager\_container\_v1.container\_1 0c6cd26a-c012-4d7b-8034-05

# » openstack\_orchestration\_stack\_v1

Manages a V1 stack resource within OpenStack.

# » Example Usage

```
resource "openstack_orchestration_stack_v1" "stack_1" {
   name = "stack_1"
   parameters = {
      length = 4
   }
   template_opts = {
      Bin = "heat_template_version: 2013-05-23\nparameters:\n length:\n }
   environment_opts = {
      Bin = "\n"
   }
   disable_rollback = true
   timeout = 30
}
```

type: number\nres

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the stack. If omitted, the region argument of the provider is used. Changing this creates a new stack.
- name (Required) A unique name for the stack. It must start with an alphabetic character. Changing this updates the stack's name.
- template\_opts (Required) Template key/value pairs to associate with the stack which contains either the template file or url. Allowed keys: Bin, URL, Files. Changing this updates the existing stack Template Opts.
- environment\_opts (Optional) Environment key/value pairs to associate
  with the stack which contains details for the environment of the stack.

Allowed keys: Bin, URL, Files. Changing this updates the existing stack Environment Opts.

- disable\_rollback (Optional) Enables or disables deletion of all stack resources when a stack creation fails. Default is true, meaning all resources are not deleted when stack creation fails.
- parameters (Optional) User-defined key/value pairs as parameters to pass to the template. Changing this updates the existing stack parameters.
- timeout (Optional) The timeout for stack action in minutes.
- tags (Optional) A list of tags to assosciate with the Stack

#### » Attributes Reference

The following attributes are exported:

- name See Argument Reference above.
- disable\_rollback See Argument Reference above.
- timeout See Argument Reference above.
- parameters See Argument Reference above.
- tags See Argument Reference above.
- capabilities List of stack capabilities for stack.
- description The description of the stack resource.
- notification\_topics List of notification topics for stack.
- status The status of the stack.
- status\_reason The reason for the current status of the stack.
- template\_description The description of the stack template.
- outputs A list of stack outputs.
- creation\_time The date and time when the resource was created. The date and time stamp format is ISO 8601: CCYY-MM-DDThh:mm:ss±hh:mm For example, 2015-08-27T09:49:58-05:00. The ±hh:mm value, if included, is the time zone as an offset from UTC.
- updated\_time The date and time when the resource was updated. The date and time stamp format is ISO 8601: CCYY-MM-DDThh:mm:ss±hh:mm For example, 2015-08-27T09:49:58-05:00. The ±hh:mm value, if included, is the time zone as an offset from UTC.

## » Import

stacks can be imported using the id, e.g.

\$ terraform import openstack\_orchestration\_stack\_v1.stack\_1 ea257959-eeb1-4c10-8d33-26f0409a