# » openstack\_compute\_flavor\_v2

Use this data source to get the ID of an available OpenStack flavor.

# » Example Usage

```
data "openstack_compute_flavor_v2" "small" {
  vcpus = 1
  ram = 512
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the flavor.
- min\_ram (Optional) The minimum amount of RAM (in megabytes).
- ram (Optional) The exact amount of RAM (in megabytes).
- min\_disk (Optional) The minimum amount of disk (in gigabytes).
- disk (Optional) The exact amount of disk (in gigabytes).
- vcpus (Optional) The amount of VCPUs.
- swap (Optional) The amount of swap (in gigabytes).
- rx\_tx\_factor (Optional) The rx\_tx\_factor of the flavor.

# » Attributes Reference

id is set to the ID of the found flavor. In addition, the following attributes are exported:

• is\_public - Whether the flavor is public or private.

# 

Use this data source to get the ID and public key of an OpenStack keypair.

# » Example Usage

```
data "openstack_compute_keypair_v2" "kp" {
  name = "sand"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used.
- name (Required) The unique name of the keypair.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- public\_key The OpenSSH-formatted public key of the keypair.

# » openstack\_dns\_zone\_v2

Use this data source to get the ID of an available OpenStack DNS zone.

## » Example Usage

```
data "openstack_dns_zone_v2" "zone_1" {
  name = "example.com"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 DNS client. A DNS client is needed to retrieve zone ids. If omitted, the region argument of the provider is used.
- name (Optional) The name of the zone.
- description (Optional) A description of the zone.
- email (Optional) The email contact for the zone record.

- status (Optional) The zone's status.
- ttl (Optional) The time to live (TTL) of the zone.
- type (Optional) The type of the zone. Can either be PRIMARY or SECONDARY.

id is set to the ID of the found zone. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- email See Argument Reference above.
- type See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- status See Argument Reference above.
- attributes Attributes of the DNS Service scheduler.
- masters An array of master DNS servers. When type is SECONDARY.
- created\_at The time the zone was created.
- updated\_at The time the zone was last updated.
- transferred\_at The time the zone was transferred.
- version The version of the zone.
- serial The serial number of the zone.
- pool\_id The ID of the pool hosting the zone.
- project\_id The project ID that owns the zone.

# » openstack\_identity\_auth\_scope\_v3

Use this data source to get authentication information about the current auth scope in use. This can be used as self-discovery or introspection of the username or project name currently in use.

## » Example Usage

```
data "openstack_identity_auth_scope_v3" "scope" {
  name = "my_scope"
}
```

# » Argument Reference

- name (Required) The name of the scope. This is an arbitrary name which is only used as a unique identifier so an actual token isn't used as the ID.
- region (Optional) The region in which to obtain the V3 Identity client. A Identity client is needed to retrieve tokens IDs. If omitted, the region argument of the provider is used.

### » Attributes Reference

id is set to the name given to the scope. In addition, the following attributes are exported:

- user\_name The username of the scope.
- user\_id The user ID the of the scope.
- user\_domain\_name The domain name of the user.
- user\_domain\_id The domain ID of the user.
- project\_name The project name of the scope.
- project\_id The project ID of the scope.
- project\_domain\_name The domain name of the project.
- project\_domain\_id The domain ID of the project.
- roles A list of roles in the current scope. See reference below.

The roles block contains:

- role\_id The ID of the role.
- role\_name The name of the role.

# ightarrow openstack\_identity\_endpoint\_v3

Use this data source to get the ID of an OpenStack endpoint.

Note: This usually requires admin privileges.

### » Example Usage

```
data "openstack_identity_endpoint_v3" "endpoint_1" {
   service_name = "demo"
}
```

## » Argument Reference

- service\_id (Optional) The service id this endpoint belongs to.
- service\_name (Optional) The service name of the endpoint.
- interface (Optional) The endpoint interface. Valid values are public, internal, and admin. Default value is public
- region (Optional) The region the endpoint is located in.

id is set to the ID of the found endpoint. In addition, the following attributes are exported:

- service\_id See Argument Reference above.
- service\_name See Argument Reference above.
- interface See Argument Reference above.
- url The endpoint URL
- region The region the endpoint is located in.

# » openstack\_identity\_group\_v3

Use this data source to get the ID of an OpenStack group.

Note: This usually requires admin privileges.

# » Example Usage

```
data "openstack_identity_group_v3" "admins" {
  name = "admins"
}
```

# » Argument Reference

- name The name of the group.
- domain\_id (Optional) The domain the group belongs to.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.

id is set to the ID of the found group. In addition, the following attributes are exported:

- name See Argument Reference above.
- domain\_id See Argument Reference above.
- region See Argument Reference above.

# » openstack\_identity\_project\_v3

Use this data source to get the ID of an OpenStack project.

## » Example Usage

```
data "openstack_identity_project_v3" "project_1" {
  name = "demo"
}
```

# » Argument Reference

The following arguments are supported:

- domain\_id (Optional) The domain this project belongs to.
- enabled (Optional) Whether the project is enabled or disabled. Valid values are true and false.
- is\_domain (Optional) Whether this project is a domain. Valid values are true and false.
- name (Optional) The name of the project.
- parent\_id (Optional) The parent of this project.

### » Attributes Reference

id is set to the ID of the found project. In addition, the following attributes are exported:

- description The description of the project.
- domain\_id See Argument Reference above.
- enabled See Argument Reference above.
- is\_domain See Argument Reference above.
- name See Argument Reference above.

- parent\_id See Argument Reference above.
- region The region the project is located in.

# » openstack\_identity\_role\_v3

Use this data source to get the ID of an OpenStack role.

# » Example Usage

```
data "openstack_identity_role_v3" "admin" {
  name = "admin"
}
```

# » Argument Reference

- name The name of the role.
- domain\_id (Optional) The domain the role belongs to.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.

### » Attributes Reference

id is set to the ID of the found role. In addition, the following attributes are exported:

- name See Argument Reference above.
- domain\_id See Argument Reference above.
- region See Argument Reference above.

# » openstack\_identity\_user\_v3

Use this data source to get the ID of an OpenStack user.

# » Example Usage

```
data "openstack_identity_user_v3" "user_1" {
  name = "user_1"
}
```

# » Argument Reference

The following arguments are supported:

- description (Optional) A description of the user.
- default\_project\_id (Optional) The default project this user belongs to.
- domain id (Optional) The domain this user belongs to.
- enabled (Optional) Whether the user is enabled or disabled. Valid values are true and false.
- idp\_id (Optional) The identity provider ID of the user.
- name (Optional) The name of the user.
- password\_expires\_at (Optional) Query for expired passwords. See the OpenStack API docs for more information on the query format.
- protocol\_id (Optional) The protocol ID of the user.
- unique\_id (Optional) The unique ID of the user.

### » Attributes Reference

The following attributes are exported:

- default\_project\_id See Argument Reference above.
- domain\_id See Argument Reference above.
- enabled See Argument Reference above.
- idp\_id See Argument Reference above.
- name See Argument Reference above.
- password\_expires\_at See Argument Reference above.
- protocol\_id See Argument Reference above.
- region The region the user is located in.
- unique\_id See Argument Reference above.

# $ightsymbol{"}$ openstack\_images\_image\_v2

Use this data source to get the ID of an available OpenStack image.

### » Example Usage

```
data "openstack_images_image_v2" "ubuntu" {
  name = "Ubuntu 16.04"
```

```
most_recent = true
properties {
   key = "value"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Glance client.
   A Glance client is needed to create an Image that can be used with a compute instance. If omitted, the region argument of the provider is used.
- most\_recent (Optional) If more than one result is returned, use the most recent image.
- name (Optional) The name of the image.
- owner (Optional) The owner (UUID) of the image.
- properties (Optional) a map of key/value pairs to match an image with. All specified properties must be matched.
- size\_min (Optional) The minimum size (in bytes) of the image to return.
- size\_max (Optional) The maximum size (in bytes) of the image to return.
- sort\_direction (Optional) Order the results in either asc or desc.
- sort\_key (Optional) Sort images based on a certain key. Defaults to name.
- tag (Optional) Search for images with a specific tag.
- visibility (Optional) The visibility of the image. Must be one of "public", "private", "community", or "shared". Defaults to "private".
- member\_status (Optional) The status of the image. Must be one of "accepted", "pending", "rejected", or "all".

#### » Attributes Reference

id is set to the ID of the found image. In addition, the following attributes are exported:

- checksum The checksum of the data associated with the image.
- created\_at The date the image was created.
- container\_format: The format of the image's container.
- disk\_format: The format of the image's disk.

- file the trailing path after the glance endpoint that represent the location of the image or the path to retrieve it.
- metadata The metadata associated with the image. Image metadata allow for meaningfully define the image properties and tags. See http://docs.openstack.org/developer/glance/metadefs-concepts.html.
- min\_disk\_gb The minimum amount of disk space required to use the image.
- min\_ram\_mb The minimum amount of ram required to use the image.
- properties Freeform information about the image.
- protected Whether or not the image is protected.
- schema The path to the JSON-schema that represent the image or image
- size\_bytes The size of the image (in bytes).
- tags See Argument Reference above.
- update at The date the image was last updated.

# » openstack\_networking\_floatingip\_v2

Use this data source to get the ID of an available OpenStack floating IP.

# » Example Usage

```
data "openstack_networking_floatingip_v2" "floatingip_1" {
  address = "192.168.0.4."
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve floating IP ids. If omitted, the region argument of the provider is used.
- address (Optional) The IP address of the floating IP.
- pool (Optional) The name of the pool from which the floating IP belongs to.
- port\_id (Optional) The ID of the port the floating IP is attached.
- fixed\_ip (Optional) The specific IP address of the internal port which should be associated with the floating IP.
- tenant\_id (Optional) The owner of the floating IP.

id is set to the ID of the found floating IP. In addition, the following attributes are exported:

• status - status of the floating IP (ACTIVE/DOWN).

# » openstack\_networking\_network\_v2

Use this data source to get the ID of an available OpenStack network.

# » Example Usage

```
data "openstack_networking_network_v2" "network" {
  name = "tf_test_network"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve networks ids. If omitted, the region argument of the provider is used.
- network\_id (Optional) The ID of the network.
- name (Optional) The name of the network.
- status (Optional) The status of the network.
- external (Optional) The external routing facility of the network.
- matching\_subnet\_cidr (Optional) The CIDR of a subnet within the network.
- tenant\_id (Optional) The owner of the network.
- availability\_zone\_hints (Optional) The availability zone candidates for the network.

### » Attributes Reference

id is set to the ID of the found network. In addition, the following attributes are exported:

- admin\_state\_up (Optional) The administrative state of the network.
- name See Argument Reference above.

- region See Argument Reference above.
- external See Argument Reference above.
- shared (Optional) Specifies whether the network resource can be accessed by any tenant or not.
- availability\_zone\_hints (Optional) The availability zone candidates for the network.

# " openstack\_networking\_secgroup\_v2

Use this data source to get the ID of an available OpenStack security group.

# » Example Usage

```
data "openstack_networking_secgroup_v2" "secgroup" {
  name = "tf_test_secgroup"
}
```

# » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client.
   A Neutron client is needed to retrieve security groups ids. If omitted, the region argument of the provider is used.
- secgroup\_id (Optional) The ID of the security group.
- name (Optional) The name of the security group.
- tenant\_id (Optional) The owner of the security group.

### » Attributes Reference

id is set to the ID of the found security group. In addition, the following attributes are exported:

- name See Argument Reference above.
- description- The description of the security group.
- region See Argument Reference above.

# » openstack\_networking\_subnet\_v2

Use this data source to get the ID of an available OpenStack subnet.

# » Example Usage

```
data "openstack_networking_subnet_v2" "subnet_1" {
  name = "subnet_1"
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve subnet ids. If omitted, the region argument of the provider is used.
- name (Optional) The name of the subnet.
- dhcp\_enabled (Optional) If the subnet has DHCP enabled.
- dhcp\_disabled (Optional) If the subnet has DHCP disabled.
- ip\_version (Optional) The IP version of the subnet (either 4 or 6).
- ipv6\_address\_mode (Optional) The IPv6 address mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- ipv6\_ra\_mode (Optional) The IPv6 Router Advertisement mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- gateway\_ip (Optional) The IP of the subnet's gateway.
- cidr (Optional) The CIDR of the subnet.
- subnet\_id (Optional) The ID of the subnet.
- subnetpool\_id (Optional) The ID of the subnetpool associated with the subnet.
- network\_id (Optional) The ID of the network the subnet belongs to.
- tenant\_id (Optional) The owner of the subnet.

#### » Attributes Reference

id is set to the ID of the found subnet. In addition, the following attributes are exported:

- allocation pools Allocation pools of the subnet.
- enable\_dhcp Whether the subnet has DHCP enabled or not.
- dns nameservers DNS Nameservers of the subnet.
- host\_routes Host Routes of the subnet.
- region See Argument Reference above.

# » openstack\_networking\_subnetpool\_v2

Use this data source to get the ID of an available OpenStack subnetpool.

### » Example Usage

```
data "openstack_networking_subnetpool_v2" "subnetpool_1" {
  name = "subnetpool_1"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to retrieve a subnetpool id. If omitted, the region argument of the provider is used.
- name (Optional) The name of the subnetpool.
- default\_quota (Optional) The per-project quota on the prefix space that can be allocated from the subnetpool for project subnets.
- project\_id (Optional) The owner of the subnetpool.
- prefixes (Optional) A list of subnet prefixes that are assigned to the subnetpool.
- default\_prefixlen (Optional) The size of the subnetpool default prefix length.
- min\_prefixlen (Optional) The size of the subnetpool min prefix length.
- max\_prefixlen (Optional) The size of the subnetpool max prefix length.
- address\_scope\_id (Optional) The Neutron address scope that subnet-pools is assigned to.
- ip\_version The IP protocol version.
- shared (Optional) Whether this subnetpool is shared across all projects.
- description (Optional) The human-readable description for the subnetpool.
- is\_default (Optional) Whether the subnetpool is default subnetpool or not.

id is set to the ID of the found subnetpool. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- default\_quota See Argument Reference above.
- project\_id See Argument Reference above.
- created\_at The time at which subnetpool was created.
- updated\_at The time at which subnetpool was created.
- prefixes See Argument Reference above.
- default\_prefixlen See Argument Reference above.
- min\_prefixlen See Argument Reference above.
- max\_prefixlen See Argument Reference above.
- address\_scope\_id See Argument Reference above.
- ip\_version -The IP protocol version.
- shared See Argument Reference above.
- description See Argument Reference above.
- is default See Argument Reference above.
- revision\_number The revision number of the subnetpool.

# » openstack blockstorage volume v1

Manages a V1 volume resource within OpenStack.

# » Example Usage

## » Argument Reference

The following arguments are supported:

• region - (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.

- size (Required) The size of the volume to create (in gigabytes). Changing this creates a new volume.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- availability\_zone (Optional) The availability zone for the volume.
   Changing this creates a new volume.
- image\_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- snapshot\_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source\_vol\_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- volume\_type (Optional) The type of volume to create. Changing this
  creates a new volume.

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- availability\_zone See Argument Reference above.
- image\_id See Argument Reference above.
- source\_vol\_id See Argument Reference above.
- snapshot\_id See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.

# » Import

Volumes can be imported using the id, e.g.

# » openstack\_blockstorage\_volume\_v2

Manages a V2 volume resource within OpenStack.

### » Example Usage

### » Argument Reference

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes). Changing this creates a new volume.
- availability\_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- consistency\_group\_id (Optional) The consistency group to place the volume in.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- image\_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- snapshot\_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.

- source\_replica (Optional) The volume ID to replicate with.
- source\_vol\_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- volume\_type (Optional) The type of volume to create. Changing this
  creates a new volume.

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- availability\_zone See Argument Reference above.
- image\_id See Argument Reference above.
- source\_vol\_id See Argument Reference above.
- snapshot\_id See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.

# » Import

Volumes can be imported using the id, e.g.

\$ terraform import openstack\_blockstorage\_volume\_v2.volume\_1 ea257959-eeb1-4c10-8d33-26f0409

# $\begin{tabular}{ll} \verb& w open stack\_block storage\_volume\_attach\_v2 \\ \end{tabular}$

This resource is experimental and may be removed in the future! Feedback is requested if you find this resource useful or if you find any problems with it.

Creates a general purpose attachment connection to a Block Storage volume using the OpenStack Block Storage (Cinder) v2 API. Depending on your Block Storage service configuration, this resource can assist in attaching a volume to a non-OpenStack resource such as a bare-metal server or a remote virtual machine in a different cloud provider.

This does not actually attach a volume to an instance. Please use the openstack\_compute\_volume\_attach\_v2 resource for that.

## » Example Usage

```
resource "openstack_blockstorage_volume_v2" "volume_1" {
   name = "volume_1"
   size = 1
}

resource "openstack_blockstorage_volume_attach_v2" "va_1" {
   volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
   device = "auto"
   host_name = "devstack"
   ip_address = "192.168.255.10"
   initiator = "iqn.1993-08.org.debian:01:e9861fb1859"
   os_type = "linux2"
   platform = "x86_64"
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Block Storage client. A Block Storage client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- attach\_mode (Optional) Specify whether to attach the volume as Read-Only (ro) or Read-Write (rw). Only values of ro and rw are accepted. If left unspecified, the Block Storage API will apply a default of rw.
- device (Optional) The device to tell the Block Storage service this volume will be attached as. This is purely for informational purposes. You can specify auto or a device such as /dev/vdc.
- host\_name (Required) The host to attach the volume to.
- initiator (Optional) The iSCSI initiator string to make the connection.
- ip\_address (Optional) The IP address of the host\_name above.
- multipath (Optional) Whether to connect to this volume via multipath.
- os\_type (Optional) The iSCSI initiator OS type.
- platform (Optional) The iSCSI initiator platform.
- volume\_id (Required) The ID of the Volume to attach to an Instance.
- wwpn (Optional) An array of wwpn strings. Used for Fibre Channel connections.

• wwnn - (Optional) A wwnn name. Used for Fibre Channel connections.

### » Attributes Reference

In addition to the above, the following attributes are exported:

- data This is a map of key/value pairs that contain the connection information. You will want to pass this information to a provisioner script to finalize the connection. See below for more information.
- driver volume type The storage driver that the volume is based on.
- mount\_point\_base A mount point base name for shared storage.

#### » Volume Connection Data

Upon creation of this resource, a data exported attribute will be available. This attribute is a set of key/value pairs that contains the information required to complete the block storage connection.

As an example, creating an iSCSI-based volume will return the following:

```
data.access_mode = rw
data.auth_method = CHAP
data.auth_password = xUhbGKQ8QCwKmHQ2
data.auth_username = Sphn5X4EoyFUUMYVYSA4
data.target_iqn = iqn.2010-10.org.openstack:volume-2d87ed25-c312-4f42-be1d-3b36b014561d
data.target_portal = 192.168.255.10:3260
data.volume_id = 2d87ed25-c312-4f42-be1d-3b36b014561d
```

This information can then be fed into a provisioner or a template shell script, where the final result would look something like:

```
iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --interface defaulticsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --login iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node -T ${self.data.target_iqn} --op update -n node -T ${self.data.target_iqn}
```

The contents of data will vary from each Block Storage service. You must have a good understanding of how the service is configured and how to make the appropriate final connection. However, if used correctly, this has the flexibility to be able to attach OpenStack Block Storage volumes to non-OpenStack resources.

# » Import

It is not possible to import this resource.

# » openstack\_blockstorage\_volume\_v3

Manages a V3 volume resource within OpenStack.

# » Example Usage

# » Argument Reference

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes).
- enable\_online\_resize (Optional) When this option is set it allows extending attached volumes. Note: updating size of an attached volume requires Cinder support for version 3.42 and a compatible storage driver.
- availability\_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- consistency\_group\_id (Optional) The consistency group to place the volume in.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- image\_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.

- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- snapshot\_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source\_replica (Optional) The volume ID to replicate with.
- source\_vol\_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- volume\_type (Optional) The type of volume to create. Changing this
  creates a new volume.

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- availability\_zone See Argument Reference above.
- image\_id See Argument Reference above.
- source\_vol\_id See Argument Reference above.
- snapshot\_id See Argument Reference above.
- metadata See Argument Reference above.
- volume\_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.

### » Import

Volumes can be imported using the id, e.g.

\$ terraform import openstack\_blockstorage\_volume\_v3.volume\_1 ea257959-eeb1-4c10-8d33-26f0409

# » openstack\_blockstorage\_volume\_attach\_v3

This resource is experimental and may be removed in the future! Feedback is requested if you find this resource useful or if you find any problems with it.

Creates a general purpose attachment connection to a Block Storage volume using the OpenStack Block Storage (Cinder) v3 API. Depending on your Block Storage service configuration, this resource can assist in attaching a volume to a

non-OpenStack resource such as a bare-metal server or a remote virtual machine in a different cloud provider.

This does not actually attach a volume to an instance. Please use the openstack\_compute\_volume\_attach\_v3 resource for that.

# » Example Usage

```
resource "openstack_blockstorage_volume_v3" "volume_1" {
   name = "volume_1"
   size = 1
}

resource "openstack_blockstorage_volume_attach_v3" "va_1" {
   volume_id = "${openstack_blockstorage_volume_v3.volume_1.id}"
   device = "auto"
   host_name = "devstack"
   ip_address = "192.168.255.10"
   initiator = "iqn.1993-08.org.debian:01:e9861fb1859"
   os_type = "linux2"
   platform = "x86_64"
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V3 Block Storage client. A Block Storage client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- attach\_mode (Optional) Specify whether to attach the volume as Read-Only (ro) or Read-Write (rw). Only values of ro and rw are accepted. If left unspecified, the Block Storage API will apply a default of rw.
- device (Optional) The device to tell the Block Storage service this volume will be attached as. This is purely for informational purposes. You can specify auto or a device such as /dev/vdc.
- host\_name (Required) The host to attach the volume to.
- initiator (Optional) The iSCSI initiator string to make the connection.
- ip\_address (Optional) The IP address of the host\_name above.
- multipath (Optional) Whether to connect to this volume via multipath.

- os\_type (Optional) The iSCSI initiator OS type.
- platform (Optional) The iSCSI initiator platform.
- volume\_id (Required) The ID of the Volume to attach to an Instance.
- wwpn (Optional) An array of wwpn strings. Used for Fibre Channel connections.
- wwnn (Optional) A wwnn name. Used for Fibre Channel connections.

In addition to the above, the following attributes are exported:

- data This is a map of key/value pairs that contain the connection information. You will want to pass this information to a provisioner script to finalize the connection. See below for more information.
- driver\_volume\_type The storage driver that the volume is based on.
- mount\_point\_base A mount point base name for shared storage.

### » Volume Connection Data

Upon creation of this resource, a data exported attribute will be available. This attribute is a set of key/value pairs that contains the information required to complete the block storage connection.

As an example, creating an iSCSI-based volume will return the following:

```
data.access_mode = rw
data.auth_method = CHAP
data.auth_password = xUhbGKQ8QCwKmHQ2
data.auth_username = Sphn5X4EoyFUUMYVYSA4
data.target_iqn = iqn.2010-10.org.openstack:volume-2d87ed25-c312-4f42-be1d-3b36b014561d
data.target_portal = 192.168.255.10:3260
data.volume_id = 2d87ed25-c312-4f42-be1d-3b36b014561d
```

This information can then be fed into a provisioner or a template shell script, where the final result would look something like:

```
iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --interface defaultiscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nod iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nod iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nod iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --login iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nod iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nod iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --rescan
```

The contents of data will vary from each Block Storage service. You must have a good understanding of how the service is configured and how to make the appropriate final connection. However, if used correctly, this has the flexibility to be able to attach OpenStack Block Storage volumes to non-OpenStack resources.

# » Import

It is not possible to import this resource.

# » openstack\_compute\_flavor\_v2

Manages a V2 flavor resource within OpenStack.

# » Example Usage

```
resource "openstack_compute_flavor_v2" "test-flavor" {
  name = "my-flavor"
  ram = "8096"
  vcpus = "2"
  disk = "20"

  extra_specs {
    "hw:cpu_policy" = "CPU-POLICY",
    "hw:cpu_thread_policy" = "CPU-THREAD-POLICY"
  }
}
```

## » Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. Flavors are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new flavor.
- name (Required) A unique name for the flavor. Changing this creates a new flavor.
- ram (Required) The amount of RAM to use, in megabytes. Changing this creates a new flavor.

- vcpus (Required) The number of virtual CPUs to use. Changing this creates a new flavor.
- disk (Required) The amount of disk space in gigabytes to use for the root (/) partition. Changing this creates a new flavor.
- swap (Optional) The amount of disk space in megabytes to use. If unspecified, the default is 0. Changing this creates a new flavor.
- rx\_tx\_factor (Optional) RX/TX bandwith factor. The default is 1. Changing this creates a new flavor.
- is\_public (Optional) Whether the flavor is public. Changing this creates a new flavor.
- extra\_specs (Optional) Key/Value pairs of metadata for the flavor.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- ram See Argument Reference above.
- vcpus See Argument Reference above.
- disk See Argument Reference above.
- swap See Argument Reference above.
- rx\_tx\_factor See Argument Reference above.
- is public See Argument Reference above.
- extra\_specs See Argument Reference above.

### » Import

Flavors can be imported using the ID, e.g.

\$ terraform import openstack\_compute\_flavor\_v2.my-flavor 4142e64b-1b35-44a0-9b1e-5affc7af110

# » openstack\_compute\_floatingip\_v2

Manages a V2 floating IP resource within OpenStack Nova (compute) that can be used for compute instances.

Please note that managing floating IPs through the OpenStack Compute API has been deprecated. Unless you are using an older OpenStack environment, it is recommended to use the openstack\_networking\_floatingip\_v2 resource instead, which uses the OpenStack Networking API.

# » Example Usage

```
resource "openstack_compute_floatingip_v2" "floatip_1" {
  pool = "public"
}
```

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a floating IP that can be used with a compute instance. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- pool (Required) The name of the pool from which to obtain the floating IP. Changing this creates a new floating IP.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- pool See Argument Reference above.
- address The actual floating IP address itself.
- fixed\_ip The fixed IP address corresponding to the floating IP.
- instance\_id UUID of the compute instance associated with the floating IP.

### » Import

Floating IPs can be imported using the id, e.g.

\$ terraform import openstack\_compute\_floatingip\_v2.floatip\_1 89c60255-9bd6-460c-822a-e2b959e

# $ightsymbol{"} ightsymbol{"} openstack\_compute\_floatingip\_associate\_v2$

Associate a floating IP to an instance. This can be used instead of the floating\_ip options in openstack\_compute\_instance\_v2.

# » Example Usage

» Automatically detect the correct network

```
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
}
resource "openstack_networking_floatingip_v2" "fip_1" {
 pool = "my_pool"
}
resource "openstack_compute_floatingip_associate_v2" "fip_1" {
  floating_ip = "${openstack_networking_floatingip_v2.fip_1.address}"
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
}
» Explicitly set the network to attach to
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
 name
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                = 3
 flavor_id
               = "my_key_pair_name"
  key_pair
  security_groups = ["default"]
 network {
   name = "my_network"
 network {
   name = "default"
 }
}
resource "openstack_networking_floatingip_v2" "fip_1" {
 pool = "my_pool"
resource "openstack_compute_floatingip_associate_v2" "fip_1" {
  floating_ip = "${openstack_networking_floatingip_v2.fip_1.address}"
```

```
instance_id = "${openstack_compute_instance_v2.instance_1.id}"
fixed_ip = "${openstack_compute_instance_v2.instance_1.network.1.fixed_ip_v4}"
}
```

# » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new floatingip\_associate.
- floating\_ip (Required) The floating IP to associate.
- instance\_id (Required) The instance to associte the floating IP with.
- fixed\_ip (Optional) The specific IP address to direct traffic to.
- wait\_until\_associated (Optional) In cases where the OpenStack environment does not automatically wait until the association has finished, set this option to have Terraform poll the instance until the floating IP has been associated. Defaults to false.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- floating\_ip See Argument Reference above.
- instance\_id See Argument Reference above.
- fixed\_ip See Argument Reference above.

### » Import

This resource can be imported by specifying all three arguments, separated by a forward slash:

\$ terraform import openstack\_compute\_floatingip\_associate\_v2.fip\_1 <floating\_ip>/<instance\_</pre>

# » openstack\_compute\_instance\_v2

Manages a V2 VM instance resource within OpenStack.

# » Example Usage

#### » Basic Instance

```
resource "openstack_compute_instance_v2" "basic" {
                 = "basic"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                 = "3"
 flavor_id
              = "my_key_pair_name"
 key_pair
  security_groups = ["default"]
 metadata {
    this = "that"
 network {
   name = "my_network"
}
» Instance With Attached Volume
resource "openstack_blockstorage_volume_v2" "myvol" {
 name = "myvol"
 size = 1
}
resource "openstack_compute_instance_v2" "myinstance" {
                 = "myinstance"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
 flavor_id
                 = "3"
                 = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 network {
   name = "my_network"
 }
}
resource "openstack_compute_volume_attach_v2" "attached" {
  compute_id = "${openstack_compute_instance_v2.myinstance.id}"
  volume_id = "${openstack_blockstorage_volume_v2.myvol.id}"
}
```

### » Boot From Volume

```
resource "openstack_compute_instance_v2" "boot-from-volume" {
                 = "boot-from-volume"
 flavor_id
                 = "3"
                 = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 block_device {
                         = "<image-id>"
   uuid
                         = "image"
   source_type
                         = 5
   volume_size
   boot_index
                         = 0
                     = "volume"
   destination_type
   delete_on_termination = true
 network {
   name = "my_network"
}
» Boot From an Existing Volume
resource "openstack_blockstorage_volume_v1" "myvol" {
          = "myvol"
 name
 size
          = 5
 image_id = "<image-id>"
resource "openstack_compute_instance_v2" "boot-from-volume" {
                = "bootfromvolume"
 name
                = "3"
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 block_device {
                         = "${openstack_blockstorage_volume_v1.myvol.id}"
   uuid
                         = "volume"
   source_type
   boot_index
                         = 0
                         = "volume"
   destination_type
   delete_on_termination = true
 network {
```

```
name = "my_network"
 }
}
» Boot Instance, Create Volume, and Attach Volume as a Block De-
vice
resource "openstack_compute_instance_v2" "instance_1" {
                = "instance_1"
 name
                = "<image-id>"
 image_id
                = "3"
 flavor_id
 key_pair = "my_key_pair_name"
 security_groups = ["default"]
 block_device {
   uuid
                         = "<image-id>"
                        = "image"
   source_type
   destination_type
                        = "local"
   boot_index
   delete_on_termination = true
 }
 block_device {
                         = "blank"
   source_type
   destination_type
                       = "volume"
   volume_size
                         = 1
   boot_index
   delete_on_termination = true
}
» Boot Instance and Attach Existing Volume as a Block Device
resource "openstack_blockstorage_volume_v2" "volume_1" {
 name = "volume_1"
 size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
 name
               = "instance_1"
                = "<image-id>"
 image_id
```

= "my\_key\_pair\_name"

= "3"

security\_groups = ["default"]

flavor\_id

key\_pair

```
block_device {
    uuid
                          = "<image-id>"
                         = "image"
    source_type
    destination_type
                         = "local"
   boot_index
   delete_on_termination = true
 }
 block_device {
                          = "${openstack_blockstorage_volume_v2.volume_1.id}"
   uuid
                          = "volume"
    source_type
                         = "volume"
   destination_type
   boot index
                          = 1
   delete_on_termination = true
}
» Instance With Multiple Networks
resource "openstack_networking_floatingip_v2" "myip" {
 pool = "my_pool"
}
resource "openstack_compute_instance_v2" "multi-net" {
                 = "multi-net"
 name
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                 = "3"
 flavor_id
 key_pair
                 = "my_key_pair_name"
 security_groups = ["default"]
 network {
   name = "my_first_network"
 network {
   name = "my_second_network"
}
resource "openstack_compute_floatingip_associate_v2" "myip" {
  floating_ip = "${openstack_networking_floatingip_v2.myip.address}"
  instance_id = "${openstack_compute_instance_v2.multi-net.id}"
  fixed_ip = "${openstack_compute_instance_v2.multi-net.network.1.fixed_ip_v4}"
}
```

### » Instance With Personality

```
resource "openstack_compute_instance_v2" "personality" {
                 = "personality"
 image_id
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
                = "3"
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 personality {
   file = "/path/to/file/on/instance.txt"
   content = "contents of file"
 }
 network {
   name = "my_network"
}
```

### » Instance with Multiple Ephemeral Disks

```
resource "openstack_compute_instance_v2" "multi-eph" {
                = "multi eph"
 name
                = "ad091b52-742f-469e-8f3c-fd81cadf0743"
 image_id
 flavor_id
                = "3"
 key_pair
                = "my_key_pair_name"
 security_groups = ["default"]
 block_device {
   boot_index
                        = 0
   delete_on_termination = true
   destination_type = "local"
                        = "image"
   source_type
                       = "<image-id>"
   uuid
 }
 block_device {
   boot_index
                        = -1
   delete_on_termination = true
   destination_type = "local"
   source_type
                        = "blank"
   volume_size
                       = 1
 }
 block_device {
```

```
boot_index = -1
delete_on_termination = true
destination_type = "local"
source_type = "blank"
volume_size = 1
}
```

## » Instance with User Data (cloud-init)

user\_data can come from a variety of sources: inline, read in from the file function, or the template\_cloudinit\_config resource.

## » Argument Reference

}

- region (Optional) The region in which to create the server instance. If omitted, the region argument of the provider is used. Changing this creates a new server.
- name (Required) A unique name for the resource.
- image\_id (Optional; Required if image\_name is empty and not booting from a volume. Do not specify if booting from a volume.) The image ID of the desired image for the server. Changing this creates a new server.
- image\_name (Optional; Required if image\_id is empty and not booting from a volume. Do not specify if booting from a volume.) The name of the desired image for the server. Changing this creates a new server.
- flavor\_id (Optional; Required if flavor\_name is empty) The flavor ID of the desired flavor for the server. Changing this resizes the existing server.

- flavor\_name (Optional; Required if flavor\_id is empty) The name of the desired flavor for the server. Changing this resizes the existing server.
- user\_data (Optional) The user data to provide when launching the instance. Changing this creates a new server.
- security\_groups (Optional) An array of one or more security group names to associate with the server. Changing this results in adding/removing security groups from the existing server. *Note*: When attaching the instance to networks using Ports, place the security groups on the Port and not the instance.
- availability\_zone (Optional) The availability zone in which to create the server. Changing this creates a new server.
- network (Optional) An array of one or more networks to attach to the instance. The network object structure is documented below. Changing this creates a new server.
- metadata (Optional) Metadata key/value pairs to make available from within the instance. Changing this updates the existing server metadata.
- config\_drive (Optional) Whether to use the config\_drive feature to configure the instance. Changing this creates a new server.
- admin\_pass (Optional) The administrative password to assign to the server. Changing this changes the root password on the existing server.
- key\_pair (Optional) The name of a key pair to put on the server. The key pair must already be created and associated with the tenant's account. Changing this creates a new server.
- block\_device (Optional) Configuration of block devices. The block\_device structure is documented below. Changing this creates a new server. You can specify multiple block devices which will create an instance with multiple disks. This configuration is very flexible, so please see the following reference for more information.
- scheduler\_hints (Optional) Provide the Nova scheduler with hints on how the instance should be launched. The available hints are described below.
- personality (Optional) Customize the personality of an instance by defining one or more files and their contents. The personality structure is described below.
- stop\_before\_destroy (Optional) Whether to try stop instance gracefully before destroying it, thus giving chance for guest OS daemons to stop correctly. If instance doesn't stop within timeout, it will be destroyed anyway.

- force\_delete (Optional) Whether to force the OpenStack instance to be forcefully deleted. This is useful for environments that have reclaim / soft deletion enabled.
- power\_state (Optional) Provide the VM state. Only 'active' and 'shutoff' are supported values. *Note*: If the initial power\_state is the shutoff
  the VM will be stopped immediately after build and the provisioners like
  remote-exec or files are not supported.

#### The network block supports:

- uuid (Required unless port or name is provided) The network UUID to attach to the server. Changing this creates a new server.
- name (Required unless unid or port is provided) The human-readable name of the network. Changing this creates a new server.
- port (Required unless unid or name is provided) The port UUID of a network to attach to the server. Changing this creates a new server.
- fixed\_ip\_v4 (Optional) Specifies a fixed IPv4 address to be used on this network. Changing this creates a new server.
- fixed\_ip\_v6 (Optional) Specifies a fixed IPv6 address to be used on this network. Changing this creates a new server.
- access\_network (Optional) Specifies if this network should be used for provisioning access. Accepts true or false. Defaults to false.

#### The block\_device block supports:

- uuid (Required unless source\_type is set to "blank") The UUID of the image, volume, or snapshot. Changing this creates a new server.
- source\_type (Required) The source type of the device. Must be one of "blank", "image", "volume", or "snapshot". Changing this creates a new server
- volume\_size The size of the volume to create (in gigabytes). Required in the following combinations: source=image and destination=volume, source=blank and destination=local, and source=blank and destination=volume. Changing this creates a new server.
- boot\_index (Optional) The boot index of the volume. It defaults to 0. Changing this creates a new server.
- destination\_type (Optional) The type that gets created. Possible values are "volume" and "local". Changing this creates a new server.
- delete\_on\_termination (Optional) Delete the volume / block device upon termination of the instance. Defaults to false. Changing this creates a new server.

### The scheduler\_hints block supports:

- group (Optional) A UUID of a Server Group. The instance will be placed into that group.
- different\_host (Optional) A list of instance UUIDs. The instance will be scheduled on a different host than all other instances.
- same\_host (Optional) A list of instance UUIDs. The instance will be scheduled on the same host of those specified.
- query (Optional) A conditional query that a compute node must pass in order to host an instance.
- target\_cell (Optional) The name of a cell to host the instance.
- build\_near\_host\_ip (Optional) An IP Address in CIDR form. The instance will be placed on a compute node that is in the same subnet.
- additional\_properties (Optional) Arbitrary key/value pairs of additional properties to pass to the scheduler.

### The personality block supports:

- file (Required) The absolute path of the destination file.
- contents (Required) The contents of the file. Limited to 255 bytes.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- access\_ip\_v4 The first detected Fixed IPv4 address or the Floating IP.
- access\_ip\_v6 The first detected Fixed IPv6 address.
- metadata See Argument Reference above.
- security\_groups See Argument Reference above.
- flavor\_id See Argument Reference above.
- flavor\_name See Argument Reference above.
- network/uuid See Argument Reference above.
- network/name See Argument Reference above.
- network/port See Argument Reference above.
- network/fixed\_ip\_v4 The Fixed IPv4 address of the Instance on that network.
- network/fixed\_ip\_v6 The Fixed IPv6 address of the Instance on that network.
- network/mac The MAC address of the NIC on that network.
- all\_metadata Contains all instance metadata, even metadata not set by Terraform.

### » Notes

#### » Multiple Ephemeral Disks

It's possible to specify multiple block\_device entries to create an instance with multiple ephemeral (local) disks. In order to create multiple ephemeral disks, the sum of the total amount of ephemeral space must be less than or equal to what the chosen flavor supports.

The following example shows how to create an instance with multiple ephemeral disks:

```
resource "openstack_compute_instance_v2" "foo" {
                 = "terraform-test"
 name
 security_groups = ["default"]
 block_device {
   boot_index
                         = 0
   delete_on_termination = true
   destination_type = "local"
                        = "image"
   source_type
                        = "<image uuid>"
   uuid
 }
 block_device {
   boot_index
   delete_on_termination = true
   destination_type = "local"
                        = "blank"
   source_type
    volume_size
 }
 block_device {
   boot_index
   delete_on_termination = true
   destination_type = "local"
                        = "blank"
   source_type
   volume_size
                         = 1
}
```

#### » Instances and Security Groups

When referencing a security group resource in an instance resource, always use the *name* of the security group. If you specify the ID of the security group, Terraform will remove and reapply the security group upon each call. This is because the OpenStack Compute API returns the names of the associated security groups and not their IDs.

Note the following example:

```
resource "openstack_networking_secgroup_v2" "sg_1" {
   name = "sg_1"
}

resource "openstack_compute_instance_v2" "foo" {
   name = "terraform-test"
   security_groups = ["${openstack_networking_secgroup_v2.sg_1.name}"]
}
```

#### » Instances and Ports

Neutron Ports are a great feature and provide a lot of functionality. However, there are some notes to be aware of when mixing Instances and Ports:

- In OpenStack environments prior to the Kilo release, deleting or recreating an Instance will cause the Instance's Port(s) to be deleted. One way of working around this is to taint any Port(s) used in Instances which are to be recreated. See here for further information.
- When attaching an Instance to one or more networks using Ports, place the security groups on the Port and not the Instance. If you place the security groups on the Instance, the security groups will not be applied upon creation, but they will be applied upon a refresh. This is a known OpenStack bug.
- Network IP information is not available within an instance for networks that are attached with Ports. This is mostly due to the flexibility Neutron Ports provide when it comes to IP addresses. For example, a Neutron Port can have multiple Fixed IP addresses associated with it. It's not possible to know which single IP address the user would want returned to the Instance's state information. Therefore, in order for a Provisioner to connect to an Instance via it's network Port, customize the connection information:

```
]
resource "openstack_compute_instance_v2" "instance_1" {
 name = "instance_1"
 network {
   port = "${openstack_networking_port_v2.port_1.id}"
  connection {
                = "root"
   user
                = "${openstack_networking_port_v2.port_1.fixed_ip.0.ip_address}"
   host
   private_key = "~/path/to/key"
 }
 provisioner "remote-exec" {
    inline = [
      "echo terraform executed > /tmp/foo",
 }
}
```

# » openstack\_compute\_keypair\_v2

Manages a V2 keypair resource within OpenStack.

Important Security Notice The private key generated by this resource will be stored *unencrypted* in your Terraform state file. Use of this resource for production deployments is *not* recommended. Instead, generate a private key file outside of Terraform and distribute it securely to the system where Terraform will be run.

### » Example Usage

### » Import an Existing Public Key

### » Generate a Public/Private Key Pair

```
resource "openstack_compute_keypair_v2" "test-keypair" {
  name = "my-keypair"
}
```

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new keypair.
- name (Required) A unique name for the keypair. Changing this creates a new keypair.
- public\_key (Optional) A pregenerated OpenSSH-formatted public key. Changing this creates a new keypair. If a public key is not specified, then a public/private key pair will be automatically generated. If a pair is created, then destroying this resource means you will lose access to that keypair forever.
- value\_specs (Optional) Map of additional options.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- public\_key See Argument Reference above.
- fingerprint The fingerprint of the public key.
- private\_key The generated private key when no public key is specified.

### » Import

Keypairs can be imported using the name, e.g.

\$ terraform import openstack\_compute\_keypair\_v2.my-keypair test-keypair

### » openstack\_compute\_secgroup\_v2

Manages a V2 security group resource within OpenStack.

Please note that managing security groups through the OpenStack Compute API has been deprecated. Unless you are using an older OpenStack environment, it is recommended to use the openstack\_networking\_secgroup\_v2 and openstack\_networking\_secgroup\_rule\_v2 resources instead, which uses the OpenStack Networking API.

### » Example Usage

```
resource "openstack_compute_secgroup_v2" "secgroup_1" {
              = "my secgroup"
 description = "my security group"
 rule {
               = 22
    from_port
    to_port
              = 22
    ip_protocol = "tcp"
               = "0.0.0.0/0"
    cidr
 rule {
    from_port
                = 80
               = 80
    to_port
    ip_protocol = "tcp"
              = "0.0.0.0/0"
    cidr
 }
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a security group. If omitted, the region argument of the provider is used. Changing this creates a new security group.
- name (Required) A unique name for the security group. Changing this updates the name of an existing security group.
- description (Required) A description for the security group. Changing this updates the description of an existing security group.

• rule - (Optional) A rule describing how the security group operates. The rule object structure is documented below. Changing this updates the security group rules. As shown in the example above, multiple rule blocks may be used.

#### The rule block supports:

- from\_port (Required) An integer representing the lower bound of the port range to open. Changing this creates a new security group rule.
- to\_port (Required) An integer representing the upper bound of the port range to open. Changing this creates a new security group rule.
- ip\_protocol (Required) The protocol type that will be allowed. Changing this creates a new security group rule.
- cidr (Optional) Required if from\_group\_id or self is empty. The IP range that will be the source of network traffic to the security group. Use 0.0.0.0/0 to allow all IP addresses. Changing this creates a new security group rule. Cannot be combined with from\_group\_id or self.
- from\_group\_id (Optional) Required if cidr or self is empty. The ID of a group from which to forward traffic to the parent group. Changing this creates a new security group rule. Cannot be combined with cidr or self.
- self (Optional) Required if cidr and from\_group\_id is empty. If true, the security group itself will be added as a source to this ingress rule. Cannot be combined with cidr or from\_group\_id.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- rule See Argument Reference above.

#### » Notes

#### » ICMP Rules

When using ICMP as the ip\_protocol, the from\_port sets the ICMP type and the to\_port sets the ICMP code. To allow all ICMP types, set each value to -1, like so:

```
rule {
  from_port = -1
  to_port = -1
  ip_protocol = "icmp"
  cidr = "0.0.0.0/0"
}
```

A list of ICMP types and codes can be found here.

### » Referencing Security Groups

When referencing a security group in a configuration (for example, a configuration creates a new security group and then needs to apply it to an instance being created in the same configuration), it is currently recommended to reference the security group by name and not by ID, like this:

### » Import

Security Groups can be imported using the id, e.g.

\$ terraform import openstack\_compute\_secgroup\_v2.my\_secgroup 1bc30ee9-9d5b-4c30-bdd5-7f1e66

# » openstack\_compute\_servergroup\_v2

Manages a V2 Server Group resource within OpenStack.

### » Example Usage

```
resource "openstack_compute_servergroup_v2" "test-sg" {
  name = "my-sg"
  policies = ["anti-affinity"]
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used. Changing this creates a new server group.
- name (Required) A unique name for the server group. Changing this creates a new server group.
- policies (Required) The set of policies for the server group. Only two two policies are available right now, and both are mutually exclusive. See the Policies section for more information. Changing this creates a new server group.
- value\_specs (Optional) Map of additional options.

#### » Policies

- affinity All instances/servers launched in this group will be hosted on the same compute node.
- anti-affinity All instances/servers launched in this group will be hosted on different compute nodes.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- policies See Argument Reference above.
- members The instances that are part of this server group.

### » Import

Server Groups can be imported using the id, e.g.

\$ terraform import openstack\_compute\_servergroup\_v2.test-sg 1bc30ee9-9d5b-4c30-bdd5-7f1e663:

# » openstack\_compute\_volume\_attach\_v2

Attaches a Block Storage Volume to an Instance using the OpenStack Compute (Nova) v2 API.

### » Example Usage

order.

» Basic attachment of a single volume to a single instance

```
resource "openstack_blockstorage_volume_v2" "volume_1" {
 name = "volume_1"
 size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance_1"
  security_groups = ["default"]
}
resource "openstack_compute_volume_attach_v2" "va_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
}
» Attaching multiple volumes to a single instance
resource "openstack_blockstorage_volume_v2" "volumes" {
  count = 2
 name = "${format("vol-%02d", count.index + 1)}"
 size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance_1"
  security_groups = ["default"]
}
resource "openstack_compute_volume_attach_v2" "attachments" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${element(openstack_blockstorage_volume_v2.volumes.*.id, count.index)}"
}
output "volume devices" {
  value = "${openstack_compute_volume_attach_v2.attachments.*.device}"
}
Note that the above example will not guarantee that the volumes are attached
in a deterministic manner. The volumes will be attached in a seemingly random
```

If you want to ensure that the volumes are attached in a given order, create explicit dependencies between the volumes, such as:

```
resource "openstack_blockstorage_volume_v2" "volumes" {
  count = 2
 name = "${format("vol-%02d", count.index + 1)}"
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance 1"
  security_groups = ["default"]
resource "openstack compute volume attach v2" "attach 1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volumes.0.id}"
}
resource "openstack_compute_volume_attach_v2" "attach_2" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
            = "${openstack_blockstorage_volume_v2.volumes.1.id}"
  depends_on = ["openstack_compute_volume_attach_v2.attach_1"]
}
output "volume devices" {
  value = "${openstack compute volume attach v2.attachments.*.device}"
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- instance\_id (Required) The ID of the Instance to attach the Volume to.
- volume\_id (Required) The ID of the Volume to attach to an Instance.
- device (Optional) The device of the volume attachment (ex: /dev/vdc). *NOTE*: Being able to specify a device is dependent upon the hypervisor in use. There is a chance that the device specified in Terraform will not be the

same device the hypervisor chose. If this happens, Terraform will wish to update the device upon subsequent applying which will cause the volume to be detached and reattached indefinitely. Please use with caution.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- instance\_id See Argument Reference above.
- volume\_id See Argument Reference above.
- device See Argument Reference above. *NOTE*: The correctness of this information is dependent upon the hypervisor in use. In some cases, this should not be used as an authoritative piece of information.

### » Import

Volume Attachments can be imported using the Instance ID and Volume ID separated by a slash, e.g.

\$ terraform import openstack\_compute\_volume\_attach\_v2.va\_1 89c60255-9bd6-460c-822a-e2b959ede

# » openstack\_db\_instance\_v1

Manages a V1 DB instance resource within OpenStack.

### » Example Usage

#### » Instance

```
resource "openstack_db_instance_v1" "test" {
   region = "region-test"
   name = "test"
   flavor_id = "31792d21-c355-4587-9290-56c1ed0ca376"
   size = 8

   network {
     uuid = "c0612505-caf2-4fb0-b7cb-56a0240a2b12"
   }

   datastore {
     version = "mysql-5.7"
```

```
type = "mysql"
}
```

The following arguments are supported:

- region (Required) The region in which to create the db instance. Changing this creates a new instance.
- name (Required) A unique name for the resource.
- flavor\_id (Required) The flavor ID of the desired flavor for the instance. Changing this creates new instance.
- configuration\_id (Optional) Configuration ID to be attached to the instance. Database instance will be rebooted when configuration is detached.
- size (Required) Specifies the volume size in GB. Changing this creates new instance.
- datastore (Required) An array of database engine type and version.
   The datastore object structure is documented below. Changing this creates a new instance.
- network (Optional) An array of one or more networks to attach to the instance. The network object structure is documented below. Changing this creates a new instance.
- user (Optional) An array of username, password, host and databases. The user object structure is documented below.
- database (Optional) An array of database name, charset and collate. The database object structure is documented below.

### The datastore block supports:

- type (Required) Database engine type to be used in new instance. Changing this creates a new instance.
- version (Required) Version of database engine type to be used in new instance. Changing this creates a new instance.

#### The network block supports:

- uuid (Required unless port is provided) The network UUID to attach to the instance. Changing this creates a new instance.
- port (Required unless uuid is provided) The port UUID of a network to attach to the instance. Changing this creates a new instance.

- fixed\_ip\_v4 (Optional) Specifies a fixed IPv4 address to be used on this network. Changing this creates a new instance.
- fixed\_ip\_v6 (Optional) Specifies a fixed IPv6 address to be used on this network. Changing this creates a new instance.

#### The user block supports:

- name (Optional) Username to be created on new instance. Changing this creates a new instance.
- password (Optional) User's password. Changing this creates a new instance.
- host (Optional) An ip address or % sign indicating what ip addresses can connect with this user credentials. Changing this creates a new instance.
- databases (Optional) A list of databases that user will have access to. If not specified, user has access to all databases on the instance. Changing this creates a new instance.

#### The database block supports:

- name (Optional) Database to be created on new instance. Changing this creates a new instance.
- collate (Optional) Database collation. Changing this creates a new instance.
- charset (Optional) Database character set. Changing this creates a new instance.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- size See Argument Reference above.
- flavor\_id See Argument Reference above.
- configuration\_id See Argument Reference above.
- datastore/type See Argument Reference above.
- datastore/version See Argument Reference above.
- network/uuid See Argument Reference above.
- network/port See Argument Reference above.
- network/fixed\_ip\_v4 The Fixed IPv4 address of the Instance on that network
- network/fixed\_ip\_v6 The Fixed IPv6 address of the Instance on that
- database/name See Argument Reference above.
- database/collate See Argument Reference above.

- database/charset See Argument Reference above.
- user/name See Argument Reference above.
- user/password See Argument Reference above.
- user/databases See Argument Reference above.
- user/host See Argument Reference above.

# $\Rightarrow$ openstack\_db\_database\_v1

Manages a V1 DB database resource within OpenStack.

### » Example Usage

#### » Database

## » Argument Reference

The following arguments are supported:

- name (Required) A unique name for the resource.
- instance\_id (Required) The ID for the database instance.

### » Attributes Reference

The following attributes are exported:

- region Openstack region resource is created in.
- name See Argument Reference above.
- instance\_id See Argument Reference above.

### » Import

Databases can be imported by using instance-id/db-name, e.g.

\$ terraform import openstack\_db\_database\_v1.mydb 7b9e3cd3-00d9-449c-b074-8439f8e274fa/mydb

# » openstack\_db\_user\_v1

Manages a V1 DB user resource within OpenStack.

### » Example Usage

#### » User

### » Argument Reference

The following arguments are supported:

- name (Required) A unique name for the resource.
- instance (Required) The ID for the database instance.
- password (Required) User's password.
- databases (Optional) A list of database user should have access to.

#### » Attributes Reference

The following attributes are exported:

- region Openstack region resource is created in.
- name See Argument Reference above.
- instance See Argument Reference above.
- password See Argument Reference above.
- databases See Argument Reference above.

# » openstack\_db\_configuration\_v1

Manages a V1 DB configuration resource within OpenStack.

### » Example Usage

### » Configuration

### » Argument Reference

The following arguments are supported:

- region (Required) The region in which to create the db instance. Changing this creates a new instance.
- name (Required) A unique name for the resource.
- description (Optional) Description of the resource.
- datastore (Required) An array of database engine type and version.
   The datastore object structure is documented below. Changing this creates resource.
- configuration (Optional) An array of configuration parameter name and value. Can be specified multiple times. The configuration object structure is documented below.

The datastore block supports:

- type (Required) Database engine type to be used with this configuration. Changing this creates a new resource.
- version (Required) Version of database engine type to be used with this configuration. Changing this creates a new resource.

The configuration block supports:

 name - (Optional) Configuration parameter name. Changing this creates a new resource. • value - (Optional) Configuration parameter value. Changing this creates a new resource.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- datastore/type See Argument Reference above.
- datastore/version See Argument Reference above.
- configuration/name See Argument Reference above.
- configuration/value See Argument Reference above.

## » openstack\_dns\_recordset\_v2

Manages a DNS record set in the OpenStack DNS Service.

### » Example Usage

### » Automatically detect the correct network

```
resource "openstack_dns_zone_v2" "example_zone" {
  name = "example.com."
  email = "email2@example.com"
  description = "a zone"
  ttl = 6000
  type = "PRIMARY"
}

resource "openstack_dns_recordset_v2" "rs_example_com" {
  zone_id = "${openstack_dns_zone_v2.example_zone.id}"
  name = "rs.example.com."
  description = "An example record set"
  ttl = 3000
  type = "A"
  records = ["10.0.0.1"]
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 DNS client. If omitted, the region argument of the provider is used. Changing this creates a new DNS record set.
- zone\_id (Required) The ID of the zone in which to create the record set. Changing this creates a new DNS record set.
- name (Required) The name of the record set. Note the . at the end of the name. Changing this creates a new DNS record set.
- type (Optional) The type of record set. Examples: "A", "MX". Changing this creates a new DNS record set.
- ttl (Optional) The time to live (TTL) of the record set.
- description (Optional) A description of the record set.
- records (Optional) An array of DNS records.
- value\_specs (Optional) Map of additional options. Changing this creates a new record set.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- type See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- records See Argument Reference above.
- zone\_id See Argument Reference above.
- value\_specs See Argument Reference above.

### » Import

This resource can be imported by specifying the zone ID and recordset ID, separated by a forward slash.

\$ terraform import openstack\_dns\_recordset\_v2.recordset\_1 <zone\_id>/<recordset\_id>

### » openstack\_dns\_zone\_v2

Manages a DNS zone in the OpenStack DNS Service.

### » Example Usage

### » Automatically detect the correct network

```
resource "openstack_dns_zone_v2" "example.com" {
  name = "example.com."
  email = "jdoe@example.com"
  description = "An example zone"
  ttl = 3000
  type = "PRIMARY"
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new DNS zone.
- name (Required) The name of the zone. Note the . at the end of the name. Changing this creates a new DNS zone.
- email (Optional) The email contact for the zone record.
- type (Optional) The type of zone. Can either be PRIMARY or SECONDARY. Changing this creates a new zone.
- attributes (Optional) Attributes for the DNS Service scheduler. Changing this creates a new zone.
- ttl (Optional) The time to live (TTL) of the zone.
- description (Optional) A description of the zone.
- masters (Optional) An array of master DNS servers. For when type is SECONDARY.
- value\_specs (Optional) Map of additional options. Changing this creates a new zone.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- email See Argument Reference above.
- type See Argument Reference above.
- attributes See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- masters See Argument Reference above.
- value\_specs See Argument Reference above.

### » Import

This resource can be imported by specifying the zone ID:

```
$ terraform import openstack_dns_zone_v2.zone_1 <zone_id>
```

# » openstack\_identity\_project\_v3

Manages a V3 Project resource within OpenStack Keystone.

Note: You *must* have admin privileges in your OpenStack cloud to use this resource.

### » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
  name = "project_1"
  description = "A project"
}
```

### » Argument Reference

- description (Optional) A description of the project.
- domain\_id (Optional) The domain this project belongs to.
- enabled (Optional) Whether the project is enabled or disabled. Valid values are true and false.

- is\_domain (Optional) Whether this project is a domain. Valid values are true and false.
- name (Optional) The name of the project.
- parent\_id (Optional) The parent of this project.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new User.

### » Attributes Reference

The following attributes are exported:

- domain\_id See Argument Reference above.
- parent\_id See Argument Reference above.

### » Import

Projects can be imported using the id, e.g.

\$ terraform import openstack\_identity\_project\_v3.project\_1 89c60255-9bd6-460c-822a-e2b959ede

# » openstack\_identity\_role\_v3

Manages a V3 Role resource within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

### » Example Usage

```
resource "openstack_identity_role_v3" "role_1" {
  name = "role_1"
}
```

### » Argument Reference

- name The name of the role.
- domain\_id (Optional) The domain the role belongs to.

• region - (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new Role.

### » Attributes Reference

The following attributes are exported:

- name See Argument Reference above.
- domain\_id See Argument Reference above.
- region See Argument Reference above.

### » Import

Roles can be imported using the id, e.g.

\$ terraform import openstack\_identity\_role\_v3.role\_1 89c60255-9bd6-460c-822a-e2b959ede9d2

# $\ \ \, \text{ ``openstack\_identity\_role\_assignment\_v3}$

Manages a V3 Role assignment within OpenStack Keystone.

Note: You *must* have admin privileges in your OpenStack cloud to use this resource.

### » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = "project_1"
}

resource "openstack_identity_user_v3" "user_1" {
   name = "user_1"
   default_project_id = "${openstack_identity_project_v3.project_1.id}"
}

resource "openstack_identity_role_v3" "role_1" {
   name = "role_1"
}

resource "openstack_identity_role_assignment_v3" "role_assignment_1" {
   user_id = "${openstack_identity_user_v3.user_1.id}"
   project_id = "${openstack_identity_project_v3.project_1.id}"
```

```
role_id = "${openstack_identity_role_v3.role_1.id}"
}
```

The following arguments are supported:

- domain\_id (Optional; Required if project\_id is empty) The domain to assign the role in.
- group\_id (Optional; Required if user\_id is empty) The group to assign
  the role to.
- project\_id (Optional; Required if domain\_id is empty) The project to assign the role in.
- user\_id (Optional; Required if group\_id is empty) The user to assign
  the role to.
- role\_id (Required) The role to assign.

#### » Attributes Reference

The following attributes are exported:

- domain\_id See Argument Reference above.
- project id See Argument Reference above.
- group\_id See Argument Reference above.
- user\_id See Argument Reference above.
- role\_id See Argument Reference above.

# » openstack\_identity\_user\_v3

Manages a V3 User resource within OpenStack Keystone.

Note: You *must* have admin privileges in your OpenStack cloud to use this resource.

### » Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = "project_1"
}
resource "openstack_identity_user_v3" "user_1" {
```

```
default_project_id = "${openstack_identity_project_v3.project_1.id}"
name = "user_1"
description = "A user"

password = "password123"

ignore_change_password_upon_first_use = true

multi_factor_auth_enabled = true

multi_factor_auth_rule {
   rule = ["password", "totp"]
}

multi_factor_auth_rule {
   rule = ["password"]
}

extra {
   email = "user_1@foobar.com"
}
```

- description (Optional) A description of the user.
- default\_project\_id (Optional) The default project this user belongs to.
- domain\_id (Optional) The domain this user belongs to.
- enabled (Optional) Whether the user is enabled or disabled. Valid values are true and false.
- extra (Optional) Free-form key/value pairs of extra information.
- ignore\_change\_password\_upon\_first\_use (Optional) User will not have to change their password upon first use. Valid values are true and false.
- ignore\_password\_expiry (Optional) User's password will not expire. Valid values are true and false.
- ignore\_lockout\_failure\_attempts (Optional) User will not have a failure lockout placed on their account. Valid values are true and false.

- multi\_factor\_auth\_enabled (Optional) Whether to enable multifactor authentication. Valid values are true and false.
- multi\_factor\_auth\_rule (Optional) A multi-factor authentication rule. The structure is documented below. Please see the Ocata release notes for more information on how to use multi-factor rules.
- name (Optional) The name of the user.
- password (Optional) The password for the user.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new User.

The multi\_factor\_auth\_rule block supports:

• rule - (Required) A list of authentication plugins that the user must authenticate with.

### » Attributes Reference

The following attributes are exported:

• domain\_id - See Argument Reference above.

### » Import

Users can be imported using the id, e.g.

\$ terraform import openstack\_identity\_user\_v3.user\_1 89c60255-9bd6-460c-822a-e2b959ede9d2

# » openstack\_images\_image\_v2

Manages a V2 Image resource within OpenStack Glance.

### » Example Usage

```
resource "openstack_images_image_v2" "rancheros" {
  name = "RancherOS"
  image_source_url = "https://releases.rancher.com/os/latest/rancheros-openstack.img"
  container_format = "bare"
  disk_format = "qcow2"
  properties {
```

```
key = "value"
}
```

- container\_format (Required) The container format. Must be one of "ami", "ari", "aki", "bare", "ovf".
- disk\_format (Required) The disk format. Must be one of "ami", "ari", "aki", "vhd", "vmdk", "raw", "qcow2", "vdi", "iso".
- local\_file\_path (Optional) This is the filepath of the raw image file that will be uploaded to Glance. Conflicts with image source url.
- image\_cache\_path (Optional) This is the directory where the images will be downloaded. Images will be stored with a filename corresponding to the url's md5 hash. Defaults to "\$HOME/.terraform/image\_cache"
- image\_source\_url (Optional) This is the url of the raw image that will be downloaded in the image\_cache\_path before being uploaded to Glance. Glance is able to download image from internet but the gophercloud library does not yet provide a way to do so. Conflicts with local\_file\_path.
- min\_disk\_gb (Optional) Amount of disk space (in GB) required to boot image. Defaults to 0.
- min\_ram\_mb (Optional) Amount of ram (in MB) required to boot image.
   Defauts to 0.
- name (Required) The name of the image.
- properties (Optional) A map of key/value pairs to set freeform information about an image.
- protected (Optional) If true, image will not be deletable. Defaults to false.
- region (Optional) The region in which to obtain the V2 Glance client. A Glance client is needed to create an Image that can be used with a compute instance. If omitted, the region argument of the provider is used. Changing this creates a new Image.
- tags (Optional) The tags of the image. It must be a list of strings. At this time, it is not possible to delete all tags of an image.
- verify\_checksum (Optional) If false, the checksum will not be verified once the image is finished uploading. Defaults to true.

• visibility - (Optional) The visibility of the image. Must be one of "public", "private", "community", or "shared". The ability to set the visibility depends upon the configuration of the OpenStack cloud.

### » Attributes Reference

The following attributes are exported:

- checksum The checksum of the data associated with the image.
- container format See Argument Reference above.
- created\_at The date the image was created.
- disk\_format See Argument Reference above.
- file the trailing path after the glance endpoint that represent the location of the image or the path to retrieve it.
- id A unique ID assigned by Glance.
- metadata The metadata associated with the image. Image metadata allow for meaningfully define the image properties and tags. See http://docs.openstack.org/developer/glance/metadefs-concepts.html.
- min\_disk\_gb See Argument Reference above.
- min\_ram\_mb See Argument Reference above.
- name See Argument Reference above.
- owner The id of the openstack user who owns the image.
- properties See Argument Reference above.
- protected See Argument Reference above.
- region See Argument Reference above.
- schema The path to the JSON-schema that represent the image or image
- size bytes The size in bytes of the data associated with the image.
- status The status of the image. It can be "queued", "active" or "saving".
- tags See Argument Reference above.
- update at The date the image was last updated.
- visibility See Argument Reference above.

### » Import

Images can be imported using the id, e.g.

\$ terraform import openstack\_images\_image\_v2.rancheros 89c60255-9bd6-460c-822a-e2b959ede9d2

# » openstack\_networking\_floatingip\_v2

Manages a V2 floating IP resource within OpenStack Neutron (networking) that can be used for load balancers. These are similar to Nova (compute) floating IP resources, but only compute floating IPs can be used with compute instances.

### » Example Usage

```
resource "openstack_networking_floatingip_v2" "floatip_1" {
  pool = "public"
}
```

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a floating IP that can be used with another networking resource, such as a load balancer. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- pool (Required) The name of the pool from which to obtain the floating IP. Changing this creates a new floating IP.
- port\_id (Optional) ID of an existing port with at least one IP address to associate with this floating IP.
- tenant\_id (Optional) The target tenant ID in which to allocate the floating IP, if you specify this together with a port\_id, make sure the target port belongs to the same tenant. Changing this creates a new floating IP (which may or may not have a different address)
- address (Optional) The actual/specific floating IP to obtain. By default, non-admin users are not able to specify a floating IP, so you must either be an admin user or have had a custom policy or role applied to your OpenStack user or project.
- fixed\_ip Fixed IP of the port to associate with this floating IP. Required if the port has multiple fixed IPs.
- subnet\_id (Optional) The subnet ID of the floating IP pool. Specify this if the floating IP network has multiple subnets.
- value specs (Optional) Map of additional options.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- pool See Argument Reference above.
- address The actual floating IP address itself.
- port\_id ID of associated port.

- tenant\_id the ID of the tenant in which to create the floating IP.
- fixed\_ip The fixed IP which the floating IP maps to.

### » Import

Floating IPs can be imported using the id, e.g.

\$ terraform import openstack\_networking\_floatingip\_v2.floatip\_1 2c7f39f3-702b-48d1-940c-b503

# » openstack\_networking\_floatingip\_associate\_v2

Associates a floating IP to a port. This is useful for situations where you have a pre-allocated floating IP or are unable to use the openstack\_networking\_floatingip\_v2 resource to create a floating IP.

### » Example Usage

```
resource "openstack_networking_port_v2" "port_1" {
  network_id = "a5bbd213-e1d3-49b6-aed1-9df60ea94b9a"
}

resource "openstack_networking_floatingip_associate_v2" "fip_1" {
  floating_ip = "1.2.3.4"
  port_id = "${openstack_networking_port_v2.port_1.id}"
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a floating IP that can be used with another networking resource, such as a load balancer. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- floating\_ip (Required) IP Address of an existing floating IP.
- port\_id (Required) ID of an existing port with at least one IP address to associate with this floating IP.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- floating\_ip See Argument Reference above.
- port\_id See Argument Reference above.

### » Import

Floating IP associations can be imported using the id of the floating IP, e.g.

\$ terraform import openstack\_networking\_floatingip\_associate\_v2.fip 2c7f39f3-702b-48d1-940c-

# » openstack\_networking\_network\_v2

Manages a V2 Neutron network resource within OpenStack.

### » Example Usage

```
resource "openstack_networking_network_v2" "network_1" {
               = "network_1"
 admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
           = "subnet_1"
 network_id = "${openstack_networking_network_v2.network_1.id}"
           = "192.168.199.0/24"
  ip_version = 4
resource "openstack_compute_secgroup_v2" "secgroup_1" {
             = "secgroup_1"
 description = "a security group"
 rule {
   from_port = 22
   to_port = 22
   ip_protocol = "tcp"
              = "0.0.0.0/0"
   cidr
}
```

```
resource "openstack_networking_port_v2" "port_1" {
  name
                     = "port 1"
                     = "${openstack_networking_network_v2.network_1.id}"
 network_id
  admin_state_up
                     = "true"
  security_group_ids = ["${openstack_compute_secgroup_v2.secgroup_1.id}"]
  fixed_ip {
    "subnet id" = "${openstack networking subnet v2.subnet 1.id}"
    "ip address" = "192.168.199.10"
 }
}
resource "openstack compute instance v2" "instance 1" {
                  = "instance 1"
 name
  security_groups = ["${openstack_compute_secgroup_v2.secgroup_1.name}"]
    port = "${openstack_networking_port_v2.port_1.id}"
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron network. If omitted, the region argument of the provider is used. Changing this creates a new network.
- name (Optional) The name of the network. Changing this updates the name of the existing network.
- shared (Optional) Specifies whether the network resource can be accessed by any tenant or not. Changing this updates the sharing capabalities of the existing network.
- external (Optional) Specifies whether the network resource has the external routing facility. Valid values are true and false. Defaults to false. Changing this updates the external attribute of the existing network.
- tenant\_id (Optional) The owner of the network. Required if admin wants to create a network for another tenant. Changing this creates a new network.
- admin\_state\_up (Optional) The administrative state of the network. Acceptable values are "true" and "false". Changing this value updates the

state of the existing network.

- segments (Optional) An array of one or more provider segment objects.
- value\_specs (Optional) Map of additional options.
- availability\_zone\_hints (Optional) An availability zone is used to make network resources highly available. Used for resources with high availability so that they are scheduled on different availability zones. Changing this creates a new network.

The segments block supports:

- physical\_network The phisical network where this network is implemented
- segmentation\_id An isolated segment on the physical network.
- network\_type The type of physical network.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- shared See Argument Reference above.
- external See Argument Reference above.
- tenant\_id See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- availability\_zone\_hints See Argument Reference above.

### » Import

Networks can be imported using the id, e.g.

\$ terraform import openstack\_networking\_network\_v2.network\_1 d90ce693-5ccf-4136-a0ed-152ce4

# » openstack\_networking\_port\_v2

Manages a V2 port resource within OpenStack.

### » Example Usage

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new port.
- name (Optional) A unique name for the port. Changing this updates the name of an existing port.
- network\_id (Required) The ID of the network to attach the port to. Changing this creates a new port.
- admin\_state\_up (Optional) Administrative up/down status for the port (must be "true" or "false" if provided). Changing this updates the admin\_state\_up of an existing port.
- mac\_address (Optional) Specify a specific MAC address for the port. Changing this creates a new port.
- tenant\_id (Optional) The owner of the Port. Required if admin wants to create a port for another tenant. Changing this creates a new port.
- device\_owner (Optional) The device owner of the Port. Changing this creates a new port.
- security\_group\_ids (Optional Conflicts with no\_security\_groups) A list of security group IDs to apply to the port. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).
- no\_security\_groups (Optional Conflicts with security\_group\_ids) If set to true, then no security groups are applied to the port. If set to false and no security\_group\_ids are specified, then the Port will yield to the default behavior of the Networking service, which is to usually apply the "default" security group.
- device\_id (Optional) The ID of the device attached to the port. Changing this creates a new port.

- fixed\_ip (Optional) An array of desired IPs for this port. The structure is described below.
- allowed\_address\_pairs (Optional) An IP/MAC Address pair of additional IP addresses that can be active on this port. The structure is described below.
- value\_specs (Optional) Map of additional options.

The fixed\_ip block supports:

- subnet\_id (Required) Subnet in which to allocate IP address for this port.
- ip\_address (Optional) IP address desired in the subnet for this port. If you don't specify ip\_address, an available IP address from the specified subnet will be allocated to this port. This field will not be populated if it is left blank. To retrieve the assigned IP address, use the all\_fixed\_ips attribute.

The allowed\_address\_pairs block supports:

- ip\_address (Required) The additional IP address.
- mac\_address (Optional) The additional MAC address.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- admin state up See Argument Reference above.
- mac address See Argument Reference above.
- tenant id See Argument Reference above.
- device\_owner See Argument Reference above.
- security\_group\_ids See Argument Reference above.
- device\_id See Argument Reference above.
- fixed\_ip See Argument Reference above.
- all\_fixed\_ips The collection of Fixed IP addresses on the port in the order returned by the Network v2 API.
- all\_security\_group\_ids The collection of Security Group IDs on the port which have been explicitly and implicitly added.

#### » Import

Ports can be imported using the id, e.g.

\$ terraform import openstack\_networking\_port\_v2.port\_1 eae26a3e-1c33-4cc1-9c31-0cd729c438a1

#### » Notes

#### » Ports and Instances

There are some notes to consider when connecting Instances to networks using Ports. Please see the openstack\_compute\_instance\_v2 documentation for further documentation.

# » openstack\_networking\_router\_interface\_v2

Manages a V2 router interface resource within OpenStack.

## » Example Usage

#### » Argument Reference

The following arguments are supported:

• region - (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a router. If omitted, the region argument of the provider is used. Changing this creates a new router interface.

- router\_id (Required) ID of the router this interface belongs to. Changing this creates a new router interface.
- subnet\_id ID of the subnet this interface connects to. Changing this creates a new router interface.
- port\_id ID of the port this interface connects to. Changing this creates a new router interface.

The following attributes are exported:

- region See Argument Reference above.
- router\_id See Argument Reference above.
- subnet id See Argument Reference above.
- port\_id See Argument Reference above.

#### » Import

Router Interfaces can be imported using the port id, e.g.

```
$ openstack port list --router <router name or id>
$ terraform import openstack_networking_router_interface_v2.int_1 <port id from above output</pre>
```

# » openstack\_networking\_router\_route\_v2

Creates a routing entry on a OpenStack V2 router.

## » Example Usage

```
= "192.168.199.0/24"
  cidr
  ip\_version = 4
}
resource "openstack_networking_router_interface_v2" "int_1" {
 router_id = "${openstack_networking_router_v2.router_1.id}"
  subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_networking_router_route_v2" "router_route_1" {
                  = ["openstack_networking_router_interface_v2.int_1"]
  depends_on
 router_id
                 = "${openstack_networking_router_v2.router_1.id}"
 destination_cidr = "10.0.1.0/24"
                   = "192.168.199.254"
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to configure a routing entry on a router. If omitted, the region argument of the provider is used. Changing this creates a new routing entry.
- router\_id (Required) ID of the router this routing entry belongs to. Changing this creates a new routing entry.
- destination\_cidr (Required) CIDR block to match on the packet's destination IP. Changing this creates a new routing entry.
- next\_hop (Required) IP address of the next hop gateway. Changing this creates a new routing entry.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- router\_id See Argument Reference above.
- destination\_cidr See Argument Reference above.
- next\_hop See Argument Reference above.

#### » Notes

The next\_hop IP address must be directly reachable from the router at the openstack\_networking\_router\_route\_v2 resource creation time. You can ensure that by explicitly specifying a dependency on the openstack\_networking\_router\_interface\_v2 resource that connects the next hop to the router, as in the example above.

## » Import

```
Routing entries can be imported using a combined ID using the following format: <router_id>-route-<destination_cidr>-<next_hop>
```

\$ terraform import openstack\_networking\_router\_route\_v2.router\_route\_1 686fe248-386c-4f70-99

# » openstack\_networking\_router\_v2

Manages a V2 router resource within OpenStack.

## » Example Usage

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a router. If omitted, the region argument of the provider is used. Changing this creates a new router.
- name (Optional) A unique name for the router. Changing this updates the name of an existing router.
- admin\_state\_up (Optional) Administrative up/down status for the router (must be "true" or "false" if provided). Changing this updates the admin\_state\_up of an existing router.

- distributed (Optional) Indicates whether or not to create a distributed router. The default policy setting in Neutron restricts usage of this property to administrative users only.
- external\_gateway (Deprecated use external\_network\_id instead)
  The network UUID of an external gateway for the router. A router with
  an external gateway is required if any compute instances or load balancers
  will be using floating IPs. Changing this updates the external gateway of
  an existing router.
- external\_network\_id (Optional) The network UUID of an external gateway for the router. A router with an external gateway is required if any compute instances or load balancers will be using floating IPs. Changing this updates the external gateway of the router.
- enable\_snat (Optional) Enable Source NAT for the router. Valid values are "true" or "false". An external\_network\_id has to be set in order to set this property. Changing this updates the enable snat of the router.
- external\_fixed\_ip (Optional) An external fixed IP for the router. This can be repeated. The structure is described below. An external\_network\_id has to be set in order to set this property. Changing this updates the external fixed IPs of the router.
- tenant\_id (Optional) The owner of the floating IP. Required if admin wants to create a router for another tenant. Changing this creates a new router.
- value specs (Optional) Map of additional driver-specific options.
- vendor\_options (Optional) Map of additional vendor-specific options. Supported options are described below.
- availability\_zone\_hints (Optional) An availability zone is used to make network resources highly available. Used for resources with high availability so that they are scheduled on different availability zones. Changing this creates a new router.

#### The external\_fixed\_ip block supports:

- subnet\_id (Optional) Subnet in which the fixed IP belongs to.
- ip\_address (Optional) The IP address to set on the router.

#### The vendor\_options block supports:

• set\_router\_gateway\_after\_create - (Optional) Boolean to control whether the Router gateway is assigned during creation or updated after creation.

The following attributes are exported:

- id ID of the router.
- region See Argument Reference above.
- name See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- external\_gateway See Argument Reference above.
- external\_network\_id See Argument Reference above.
- enable\_snat See Argument Reference above.
- external\_fixed\_ip See Argument Reference above.
- tenant\_id See Argument Reference above.
- value\_specs See Argument Reference above.
- availability\_zone\_hints See Argument Reference above.

#### » Import

Routers can be imported using the id, e.g.

\$ terraform import openstack\_networking\_router\_v2.router\_1 014395cd-89fc-4c9b-96b7-13d1ee79c

# » openstack\_networking\_subnet\_v2

Manages a V2 Neutron subnet resource within OpenStack.

### » Example Usage

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron subnet. If omitted, the region argument of the provider is used. Changing this creates a new subnet.
- network\_id (Required) The UUID of the parent network. Changing this
  creates a new subnet.
- cidr (Optional) CIDR representing IP range for this subnet, based on IP version. You can omit this option if you are creating a subnet from a subnet pool.
- ip\_version (Optional) IP version, either 4 (default) or 6. Changing this creates a new subnet.
- ipv6\_address\_mode (Optional) The IPv6 address mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- ipv6\_ra\_mode (Optional) The IPv6 Router Advertisement mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- name (Optional) The name of the subnet. Changing this updates the name of the existing subnet.
- tenant\_id (Optional) The owner of the subnet. Required if admin wants to create a subnet for another tenant. Changing this creates a new subnet.
- allocation\_pools (Optional) An array of sub-ranges of CIDR available for dynamic allocation to ports. The allocation\_pool object structure is documented below. Changing this creates a new subnet.
- gateway\_ip (Optional) Default gateway used by devices in this subnet. Leaving this blank and not setting no\_gateway will cause a default gateway of .1 to be used. Changing this updates the gateway IP of the existing subnet.
- no\_gateway (Optional) Do not set a gateway IP on this subnet. Changing this removes or adds a default gateway IP of the existing subnet.
- enable\_dhcp (Optional) The administrative state of the network. Acceptable values are "true" and "false". Changing this value enables or disables the DHCP capabilities of the existing subnet. Defaults to true.
- dns\_nameservers (Optional) An array of DNS name server names used by hosts in this subnet. Changing this updates the DNS name servers for the existing subnet.
- host\_routes (Optional) An array of routes that should be used by devices with IPs from this subnet (not including local subnet route). The host\_route object structure is documented below. Changing this updates the host routes for the existing subnet.

- subnetpool\_id (Optional) The ID of the subnetpool associated with the subnet.
- value\_specs (Optional) Map of additional options.

The allocation\_pools block supports:

- start (Required) The starting address.
- end (Required) The ending address.

The host\_routes block supports:

- destination\_cidr (Required) The destination CIDR.
- next\_hop (Required) The next hop in the route.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- network\_id See Argument Reference above.
- cidr See Argument Reference above.
- ip\_version See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- allocation\_pools See Argument Reference above.
- gateway\_ip See Argument Reference above.
- enable\_dhcp See Argument Reference above.
- dns\_nameservers See Argument Reference above.
- host\_routes See Argument Reference above.
- subnetpool\_id See Argument Reference above.

#### » Import

Subnets can be imported using the id, e.g.

\$ terraform import openstack\_networking\_subnet\_v2.subnet\_1 da4faf16-5546-41e4-8330-4d0002b74

# » openstack\_networking\_subnet\_route\_v2

Creates a routing entry on a OpenStack V2 subnet.

## » Example Usage

```
resource "openstack_networking_router_v2" "router_1" {
                = "router 1"
  admin_state_up = "true"
}
resource "openstack networking network v2" "network 1" {
                = "network 1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
 network_id = "${openstack_networking_network_v2.network_1.id}"
            = "192.168.199.0/24"
  ip\_version = 4
}
resource "openstack_networking_subnet_route_v2" "subnet_route_1" {
  subnet id
             = "${openstack networking subnet v2.subnet 1.id}"
 destination_cidr = "10.0.1.0/24"
                 = "192.168.199.254"
 next hop
}
```

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to configure a routing entry on a subnet. If omitted, the region argument of the provider is used. Changing this creates a new routing entry.
- subnet\_id (Required) ID of the subnet this routing entry belongs to. Changing this creates a new routing entry.
- destination\_cidr (Required) CIDR block to match on the packet's destination IP. Changing this creates a new routing entry.
- next\_hop (Required) IP address of the next hop gateway. Changing this creates a new routing entry.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- subnet\_id See Argument Reference above.
- destination\_cidr See Argument Reference above.
- next\_hop See Argument Reference above.

#### » Notes

#### » Import

Routing entries can be imported using a combined ID using the following format: <subnet\_id>-route-<destination\_cidr>-<next\_hop>

\$ terraform import openstack\_networking\_subnet\_route\_v2.subnet\_route\_1 686fe248-386c-4f70-99

# » openstack\_networking\_subnetpool\_v2

Manages a V2 Neutron subnetpool resource within OpenStack.

### » Example Usage

#### » Create a Subnet Pool

```
resource "openstack_networking_subnetpool_v2" "subnetpool_1" {
  name = "subnetpool_1"
  ip_version = 6
  prefixes = ["fdf7:b13d:dead:beef::/64", "fd65:86cc:a334:39b7::/64"]
}
```

## » Create a Subnet from a Subnet Pool

```
resource "openstack_networking_network_v2" "network_1" {
   name = "network_1"
   admin_state_up = "true"
}

resource "openstack_networking_subnetpool_v2" "subnetpool_1" {
   name = "subnetpool_1"
   prefixes = ["10.11.12.0/24"]
}

resource "openstack_networking_subnet_v2" "subnet_1" {
   name = "subnet_1"
```

```
cidr = "10.11.12.0/25"
network_id = "${openstack_networking_network_v2.network_1.id}"
subnetpool_id = "${openstack_networking_subnetpool_v2.subnetpool_1.id}"
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron subnetpool. If omitted, the region argument of the provider is used. Changing this creates a new subnetpool.
- name (Required) The name of the subnetpool. Changing this updates the name of the existing subnetpool.
- default\_quota (Optional) The per-project quota on the prefix space that can be allocated from the subnetpool for project subnets. Changing this updates the default quota of the existing subnetpool.
- project\_id (Optional) The owner of the subnetpool. Required if admin wants to create a subnetpool for another project. Changing this creates a new subnetpool.
- prefixes (Required) A list of subnet prefixes to assign to the subnetpool. Neutron API merges adjacent prefixes and treats them as a single prefix. Each subnet prefix must be unique among all subnet prefixes in all subnetpools that are associated with the address scope. Changing this updates the prefixes list of the existing subnetpool.
- default\_prefixlen (Optional) The size of the prefix to allocate when
  the cidr or prefixlen attributes are omitted when you create the subnet.
  Defaults to the MinPrefixLen. Changing this updates the default prefixlen
  of the existing subnetpool.
- min\_prefixlen (Optional) The smallest prefix that can be allocated from a subnetpool. For IPv4 subnetpools, default is 8. For IPv6 subnetpools, default is 64. Changing this updates the min prefixlen of the existing subnetpool.
- max\_prefixlen (Optional) The maximum prefix size that can be allocated from the subnetpool. For IPv4 subnetpools, default is 32. For IPv6 subnetpools, default is 128. Changing this updates the max prefixlen of the existing subnetpool.
- address\_scope\_id (Optional) The Neutron address scope to assign to the subnetpool. Changing this updates the address scope id of the existing subnetpool.

- shared (Optional) Indicates whether this subnetpool is shared across all projects. Changing this updates the shared status of the existing subnetpool.
- description (Optional) The human-readable description for the subnetpool. Changing this updates the description of the existing subnetpool.
- is\_default (Optional) Indicates whether the subnetpool is default subnetpool or not. Changing this updates the default status of the existing subnetpool.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- default\_quota See Argument Reference above.
- project\_id See Argument Reference above.
- created\_at The time at which subnetpool was created.
- updated\_at The time at which subnetpool was created.
- prefixes See Argument Reference above.
- default\_prefixlen See Argument Reference above.
- min\_prefixlen See Argument Reference above.
- max\_prefixlen See Argument Reference above.
- address\_scope\_id See Argument Reference above.
- ip\_version The IP protocol version.
- shared See Argument Reference above.
- description See Argument Reference above.
- is\_default See Argument Reference above.
- revision\_number The revision number of the subnetpool.
- value\_specs See Argument Reference above.

#### » Import

Subnetpools can be imported using the id, e.g.

\$ terraform import openstack\_networking\_subnetpool\_v2.subnetpool\_1 832cb7f3-59fe-40cf-8f64-8

# » openstack\_networking\_secgroup\_v2

Manages a V2 neutron security group resource within OpenStack. Unlike Nova security groups, neutron separates the group from the rules and also allows an

admin to target a specific tenant\_id.

### » Example Usage

### » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new security group.
- name (Required) A unique name for the security group.
- description (Optional) A unique name for the security group.
- tenant\_id (Optional) The owner of the security group. Required if admin wants to create a port for another tenant. Changing this creates a new security group.
- delete\_default\_rules (Optional) Whether or not to delete the default egress security rules. This is false by default. See the below note for more information.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- tenant\_id See Argument Reference above.

### » Default Security Group Rules

In most cases, OpenStack will create some egress security group rules for each new security group. These security group rules will not be managed by Terraform, so if you prefer to have *all* aspects of your infrastructure managed by

Terraform, set delete\_default\_rules to true and then create separate security group rules such as the following:

```
resource "openstack_networking_secgroup_rule_v2" "secgroup_rule_v4" {
   direction = "egress"
   ethertype = "IPv4"
   security_group_id = "${openstack_networking_secgroup_v2.secgroup.id}"
}

resource "openstack_networking_secgroup_rule_v2" "secgroup_rule_v6" {
   direction = "egress"
   ethertype = "IPv6"
   security_group_id = "${openstack_networking_secgroup_v2.secgroup.id}"
}
```

Please note that this behavior may differ depending on the configuration of the OpenStack cloud. The above illustrates the current default Neutron behavior. Some OpenStack clouds might provide additional rules and some might not provide any rules at all (in which case the delete\_default\_rules setting is moot).

#### » Import

Security Groups can be imported using the id, e.g.

\$ terraform import openstack\_networking\_secgroup\_v2.secgroup\_1 38809219-5e8a-4852-9139-6f46

# » openstack\_networking\_secgroup\_rule\_v2

Manages a V2 neutron security group rule resource within OpenStack. Unlike Nova security groups, neutron separates the group from the rules and also allows an admin to target a specific tenant\_id.

## » Example Usage

```
port_range_min = 22
port_range_max = 22
remote_ip_prefix = "0.0.0.0/0"
security_group_id = "${openstack_networking_secgroup_v2.secgroup_1.id}"
```

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new security group rule.
- direction (Required) The direction of the rule, valid values are **ingress** or **egress**. Changing this creates a new security group rule.
- ethertype (Required) The layer 3 protocol type, valid values are **IPv4** or **IPv6**. Changing this creates a new security group rule.
- protocol (Optional) The layer 4 protocol type, valid values are following. Changing this creates a new security group rule. This is required if you want to specify a port range.
  - tcp
  - udp
  - icmp
  - -ah
  - dccp
  - egp
  - esp
  - gre
  - igmp
  - ipv6-encap
  - ipv6-frag
  - ipv6-icmp
  - ipv6-nonxt
  - ipv6-opts
  - ipv6-route
  - ospf
  - pgm
  - rsvp
  - sctp
  - udplite
  - vrrp

- port\_range\_min (Optional) The lower part of the allowed port range, valid integer value needs to be between 1 and 65535. Changing this creates a new security group rule.
- port\_range\_max (Optional) The higher part of the allowed port range, valid integer value needs to be between 1 and 65535. Changing this creates a new security group rule.
- remote\_ip\_prefix (Optional) The remote CIDR, the value needs to be a valid CIDR (i.e. 192.168.0.0/16). Changing this creates a new security group rule.
- remote\_group\_id (Optional) The remote group id, the value needs to be an Openstack ID of a security group in the same tenant. Changing this creates a new security group rule.
- security\_group\_id (Required) The security group id the rule should belong to, the value needs to be an Openstack ID of a security group in the same tenant. Changing this creates a new security group rule.
- tenant\_id (Optional) The owner of the security group. Required if admin wants to create a port for another tenant. Changing this creates a new security group rule.

The following attributes are exported:

- region See Argument Reference above.
- direction See Argument Reference above.
- ethertype See Argument Reference above.
- protocol See Argument Reference above.
- port\_range\_min See Argument Reference above.
- port\_range\_max See Argument Reference above.
- remote\_ip\_prefix See Argument Reference above.
- remote\_group\_id See Argument Reference above.
- security\_group\_id See Argument Reference above.
- tenant\_id See Argument Reference above.

#### » Import

Security Group Rules can be imported using the id, e.g.

\$ terraform import openstack\_networking\_secgroup\_rule\_v2.secgroup\_rule\_1 aeb68ee3-6e9d-4256

# » openstack\_lb\_member\_v1

Manages a V1 load balancer member resource within OpenStack.

#### » Example Usage

```
resource "openstack_lb_member_v1" "member_1" {
  pool_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"
  address = "192.168.0.10"
  port = 80
}
```

## » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB member. If omitted, the region argument of the provider is used. Changing this creates a new LB member.
- pool\_id (Required) The ID of the LB pool. Changing this creates a new member.
- address (Required) The IP address of the member. Changing this creates a new member.
- port (Required) An integer representing the port on which the member is hosted. Changing this creates a new member.
- admin\_state\_up (Optional) The administrative state of the member. Acceptable values are 'true' and 'false'. Changing this value updates the state of the existing member.
- tenant\_id (Optional) The owner of the member. Required if admin wants to create a member for another tenant. Changing this creates a new member.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- pool\_id See Argument Reference above.
- address See Argument Reference above.
- port See Argument Reference above.

- admin\_state\_up See Argument Reference above.
- weight The load balancing weight of the member. This is currently unable to be set through Terraform.

#### » Import

Load Balancer Members can be imported using the id, e.g.

\$ terraform import openstack\_lb\_member\_v1.member\_1 a7498676-4fe4-4243-a864-2eaaf18c73df

# » openstack\_lb\_monitor\_v1

Manages a V1 load balancer monitor resource within OpenStack.

### » Example Usage

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB monitor. If omitted, the region argument of the provider is used. Changing this creates a new LB monitor.
- type (Required) The type of probe, which is PING, TCP, HTTP, or HTTPS, that is sent by the monitor to verify the member state. Changing this creates a new monitor.
- delay (Required) The time, in seconds, between sending probes to members. Changing this creates a new monitor.
- timeout (Required) Maximum number of seconds for a monitor to wait for a ping reply before it times out. The value must be less than the delay value. Changing this updates the timeout of the existing monitor.

- max\_retries (Required) Number of permissible ping failures before changing the member's status to INACTIVE. Must be a number between 1 and 10. Changing this updates the max\_retries of the existing monitor.
- url\_path (Optional) Required for HTTP(S) types. URI path that will be accessed if monitor type is HTTP or HTTPS. Changing this updates the url path of the existing monitor.
- http\_method (Optional) Required for HTTP(S) types. The HTTP method used for requests by the monitor. If this attribute is not specified, it defaults to "GET". Changing this updates the http\_method of the existing monitor.
- expected\_codes (Optional) equired for HTTP(S) types. Expected HTTP codes for a passing HTTP(S) monitor. You can either specify a single status like "200", or a range like "200-202". Changing this updates the expected codes of the existing monitor.
- admin\_state\_up (Optional) The administrative state of the monitor. Acceptable values are "true" and "false". Changing this value updates the state of the existing monitor.
- tenant\_id (Optional) The owner of the monitor. Required if admin wants to create a monitor for another tenant. Changing this creates a new monitor.

The following attributes are exported:

- region See Argument Reference above.
- type See Argument Reference above.
- delay See Argument Reference above.
- timeout See Argument Reference above.
- max\_retries See Argument Reference above.
- url\_path See Argument Reference above.
- http\_method See Argument Reference above.
- expected\_codes See Argument Reference above.
- $\bullet \;$  admin\_state\_up See Argument Reference above.
- tenant\_id See Argument Reference above.

#### » Import

Load Balancer Members can be imported using the id, e.g.

\$ terraform import openstack\_lb\_monitor\_v1.monitor\_1 119d7530-72e9-449a-aa97-124a5ef1992c

# » openstack\_lb\_pool\_v1

Manages a V1 load balancer pool resource within OpenStack.

## » Example Usage

## » Complete Load Balancing Stack Example

```
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
 admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
 network_id = "${openstack_networking_network_v2.network_1.id}"
           = "192.168.199.0/24"
 ip\_version = 4
}
resource "openstack_compute_secgroup_v2" "secgroup_1" {
            = "secgroup_1"
 description = "Rules for secgroup_1"
 rule {
   from_port = -1
   to_port = -1
   ip_protocol = "icmp"
   cidr
           = "0.0.0.0/0"
 }
 rule {
   from_port = 80
   to_port = 80
   ip_protocol = "tcp"
         = "0.0.0.0/0"
   cidr
```

```
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
  security_groups = ["default", "${openstack_compute_secgroup_v2.secgroup_1.name}"]
 network {
   uuid = "${openstack_networking_network_v2.network_1.id}"
 }
}
resource "openstack_compute_instance_v2" "instance_2" {
                 = "instance 2"
 security_groups = ["default", "${openstack_compute_secgroup_v2.secgroup_1.name}"]
 network {
    uuid = "${openstack_networking_network_v2.network_1.id}"
 }
}
resource "openstack_lb_monitor_v1" "monitor_1" {
                = "TCP"
  type
                = 30
 delay
 timeout
               = 5
 max_retries = 3
 admin_state_up = "true"
resource "openstack_lb_pool_v1" "pool_1" {
 name
            = "pool_1"
             = "TCP"
 protocol
 subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
 lb_method = "ROUND_ROBIN"
 monitor_ids = ["${openstack_lb_monitor_v1.monitor_1.id}"]
}
resource "openstack_lb_member_v1" "member_1" {
  pool_id = "${openstack_lb_pool_v1.pool_1.id}"
  address = "${openstack_compute_instance_v2.instance_1.access_ip_v4}"
 port
         = 80
}
resource "openstack_lb_member_v1" "member_2" {
 pool_id = "${openstack_lb_pool_v1.pool_1.id}"
  address = "${openstack_compute_instance_v2.instance_2.access_ip_v4}"
```

```
port = 80
}

resource "openstack_lb_vip_v1" "vip_1" {
  name = "vip_1"
  subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
  protocol = "TCP"
  port = 80
  pool_id = "${openstack_lb_pool_v1.pool_1.id}"
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB pool. If omitted, the region argument of the provider is used. Changing this creates a new LB pool.
- name (Required) The name of the pool. Changing this updates the name of the existing pool.
- protocol (Required) The protocol used by the pool members, you can use either 'TCP, 'HTTP', or 'HTTPS'. Changing this creates a new pool.
- subnet\_id (Required) The network on which the members of the pool will be located. Only members that are on this network can be added to the pool. Changing this creates a new pool.
- lb\_method (Required) The algorithm used to distribute load between the members of the pool. The current specification supports 'ROUND\_ROBIN' and 'LEAST\_CONNECTIONS' as valid values for this attribute.
- lb\_provider (Optional) The backend load balancing provider. For example: haproxy, F5, etc.
- tenant\_id (Optional) The owner of the pool. Required if admin wants to create a pool member for another tenant. Changing this creates a new pool.
- monitor\_ids (Optional) A list of IDs of monitors to associate with the pool.
- member (Optional) An existing node to add to the pool. Changing this updates the members of the pool. The member object structure is documented below. Please note that the member block is deprecated in favor of the openstack 1b member v1 resource.

The member block supports:

- address (Required) The IP address of the member. Changing this creates a new member.
- port (Required) An integer representing the port on which the member is hosted. Changing this creates a new member.
- admin\_state\_up (Required) The administrative state of the member. Acceptable values are 'true' and 'false'. Changing this value updates the state of the existing member.
- tenant\_id (Optional) The owner of the member. Required if admin wants to create a pool member for another tenant. Changing this creates a new member.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- protocol See Argument Reference above.
- subnet\_id See Argument Reference above.
- 1b\_method See Argument Reference above.
- lb\_provider See Argument Reference above.
- tenant\_id See Argument Reference above.
- monitor\_id See Argument Reference above.
- member See Argument Reference above.

#### » Notes

The member block is deprecated in favor of the openstack\_lb\_member\_v1 resource.

#### » Import

Load Balancer Pools can be imported using the id, e.g.

\$ terraform import openstack\_lb\_pool\_v1.pool\_1 b255e6ba-02ad-43e6-8951-3428ca26b713

# » openstack\_lb\_vip\_v1

Manages a V1 load balancer vip resource within OpenStack.

### » Example Usage

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VIP. If omitted, the region argument of the provider is used. Changing this creates a new VIP.
- name (Required) The name of the vip. Changing this updates the name of the existing vip.
- subnet\_id (Required) The network on which to allocate the vip's address. A tenant can only create vips on networks authorized by policy (e.g. networks that belong to them or networks that are shared). Changing this creates a new vip.
- protocol (Required) The protocol can be either 'TCP, 'HTTP', or HTTPS'. Changing this creates a new vip.
- port (Required) The port on which to listen for client traffic. Changing this creates a new vip.
- pool\_id (Required) The ID of the pool with which the vip is associated. Changing this updates the pool\_id of the existing vip.
- tenant\_id (Optional) The owner of the vip. Required if admin wants to create a vip member for another tenant. Changing this creates a new vip.
- address (Optional) The IP address of the vip. Changing this creates a new vip.
- description (Optional) Human-readable description for the vip. Changing this updates the description of the existing vip.
- persistence (Optional) Omit this field to prevent session persistence. The persistence object structure is documented below. Changing this updates the persistence of the existing vip.

- conn\_limit (Optional) The maximum number of connections allowed for the vip. Default is -1, meaning no limit. Changing this updates the conn\_limit of the existing vip.
- floating\_ip (Optional) A Networking Floating IP that will be associated with the vip. The Floating IP must be provisioned already.
- admin\_state\_up (Optional) The administrative state of the vip. Acceptable values are "true" and "false". Changing this value updates the state of the existing vip.

The persistence block supports:

- type (Required) The type of persistence mode. Valid values are "SOURCE\_IP", "HTTP\_COOKIE", or "APP\_COOKIE".
- cookie\_name (Optional) The name of the cookie if persistence mode is set appropriately.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- subnet\_id See Argument Reference above.
- protocol See Argument Reference above.
- port See Argument Reference above.
- pool\_id See Argument Reference above.
- tenant id See Argument Reference above.
- address See Argument Reference above.
- description See Argument Reference above.
- persistence See Argument Reference above.
- conn\_limit See Argument Reference above.
- floating\_ip See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- port\_id Port UUID for this VIP at associated floating IP (if any).

#### » Import

Load Balancer VIPs can be imported using the id, e.g.

\$ terraform import openstack lb vip v1.vip 1 50e16b26-89c1-475e-a492-76167182511e

# » openstack\_lb\_loadbalancer\_v2

Manages a V2 loadbalancer resource within OpenStack.

#### » Example Usage

```
resource "openstack_lb_loadbalancer_v2" "lb_1" {
    vip_subnet_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"
}
```

#### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB member. If omitted, the region argument of the provider is used. Changing this creates a new LB member.
- vip\_subnet\_id (Required) The network on which to allocate the Load-balancer's address. A tenant can only create Loadbalancers on networks authorized by policy (e.g. networks that belong to them or networks that are shared). Changing this creates a new loadbalancer.
- name (Optional) Human-readable name for the Loadbalancer. Does not have to be unique.
- description (Optional) Human-readable description for the Loadbal-ancer.
- tenant\_id-(Optional) Required for admins. The UUID of the tenant who owns the Loadbalancer. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new loadbalancer.
- vip\_address (Optional) The ip address of the load balancer. Changing this creates a new loadbalancer.
- admin\_state\_up (Optional) The administrative state of the Loadbalancer. A valid value is true (UP) or false (DOWN).
- flavor (Optional) The UUID of a flavor. Changing this creates a new loadbalancer.
- loadbalancer\_provider (Optional) The name of the provider. Changing this creates a new loadbalancer.
- security\_group\_ids (Optional) A list of security group IDs to apply to the loadbalancer. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).

The following attributes are exported:

- region See Argument Reference above.
- vip\_subnet\_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- tenant id See Argument Reference above.
- vip\_address See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- flavor See Argument Reference above.
- loadbalancer\_provider See Argument Reference above.
- security\_group\_ids See Argument Reference above.
- vip\_port\_id The Port ID of the Load Balancer IP.

# » openstack\_lb\_listener\_v2

Manages a V2 listener resource within OpenStack.

## » Example Usage

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new Listener.
- protocol (Required) The protocol can either be TCP, HTTP, HTTPS or TERMINATED\_HTTPS. Changing this creates a new Listener.
- protocol\_port (Required) The port on which to listen for client traffic. Changing this creates a new Listener.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the Listener. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new Listener.

- loadbalancer\_id (Required) The load balancer on which to provision this Listener. Changing this creates a new Listener.
- name (Optional) Human-readable name for the Listener. Does not have to be unique.
- default\_pool\_id (Optional) The ID of the default pool with which the Listener is associated. Changing this creates a new Listener.
- description (Optional) Human-readable description for the Listener.
- connection\_limit (Optional) The maximum number of connections allowed for the Listener.
- default\_tls\_container\_ref (Optional) A reference to a Barbican Secrets container which stores TLS information. This is required if the protocol is TERMINATED\_HTTPS. See here for more information.
- sni\_container\_refs (Optional) A list of references to Barbican Secrets containers which store SNI information. See here for more information.
- admin\_state\_up (Optional) The administrative state of the Listener. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the Listener.
- protocol See Argument Reference above.
- protocol port See Argument Reference above.
- tenant id See Argument Reference above.
- name See Argument Reference above.
- default\_port\_id See Argument Reference above.
- description See Argument Reference above.
- connection\_limit See Argument Reference above.
- default\_tls\_container\_ref See Argument Reference above.
- sni\_container\_refs See Argument Reference above.
- admin\_state\_up See Argument Reference above.

# ightarrow openstack\_lb\_pool\_v2

Manages a V2 pool resource within OpenStack.

### » Example Usage

```
resource "openstack_lb_pool_v2" "pool_1" {
  protocol = "HTTP"
  lb_method = "ROUND_ROBIN"
  listener_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"

  persistence {
    type = "HTTP_COOKIE"
    cookie_name = "testCookie"
  }
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new pool.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the pool. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new pool.
- name (Optional) Human-readable name for the pool.
- description (Optional) Human-readable description for the pool.
- protocol = (Required) The protocol can either be TCP, HTTP, HTTPS or PROXY. Changing this creates a new pool.
- loadbalancer\_id (Optional) The load balancer on which to provision this pool. Changing this creates a new pool. Note: One of LoadbalancerID or ListenerID must be provided.
- listener\_id (Optional) The Listener on which the members of the pool will be associated with. Changing this creates a new pool. Note: One of LoadbalancerID or ListenerID must be provided.
- 1b\_method (Required) The load balancing algorithm to distribute traffic to the pool's members. Must be one of ROUND\_ROBIN, LEAST CONNECTIONS, or SOURCE IP.
- persistence Omit this field to prevent session persistence. Indicates whether connections in the same session will be processed by the same Pool member or not. Changing this creates a new pool.
- admin\_state\_up (Optional) The administrative state of the pool. A valid value is true (UP) or false (DOWN).

The persistence argument supports:

- type (Required) The type of persistence mode. The current specification supports SOURCE IP, HTTP COOKIE, and APP COOKIE.
- cookie\_name (Optional) The name of the cookie if persistence mode is set appropriately. Required if type = APP\_COOKIE.

#### » Attributes Reference

The following attributes are exported:

- id The unique ID for the pool.
- tenant id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- protocol See Argument Reference above.
- lb\_method See Argument Reference above.
- persistence See Argument Reference above.
- admin\_state\_up See Argument Reference above.

# » openstack\_lb\_member\_v2

Manages a V2 member resource within OpenStack.

### » Example Usage

```
resource "openstack_lb_member_v2" "member_1" {
  address = "192.168.199.23"
  protocol_port = 8080
}
```

### » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new member.
- pool\_id (Required) The id of the pool that this member will be assigned to
- subnet\_id (Optional) The subnet in which to access the member

- name (Optional) Human-readable name for the member.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the member. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new member.
- address (Required) The IP address of the member to receive traffic from the load balancer. Changing this creates a new member.
- protocol\_port (Required) The port on which to listen for client traffic. Changing this creates a new member.
- weight (Optional) A positive integer value that indicates the relative portion of traffic that this member should receive from the pool. For example, a member with a weight of 10 receives five times as much traffic as a member with a weight of 2.
- admin\_state\_up (Optional) The administrative state of the member. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the member.
- name See Argument Reference above.
- weight See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- tenant\_id See Argument Reference above.
- subnet id See Argument Reference above.
- pool id See Argument Reference above.
- address See Argument Reference above.
- protocol\_port See Argument Reference above.

# » openstack\_lb\_monitor\_v2

Manages a V2 monitor resource within OpenStack.

#### » Example Usage

```
max_retries = 5
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new monitor.
- pool\_id (Required) The id of the pool that this monitor will be assigned to.
- name (Optional) The Name of the Monitor.
- tenant\_id (Optional) Required for admins. The UUID of the tenant who owns the monitor. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new monitor.
- type (Required) The type of probe, which is PING, TCP, HTTP, or HTTPS, that is sent by the load balancer to verify the member state. Changing this creates a new monitor.
- delay (Required) The time, in seconds, between sending probes to members.
- timeout (Required) Maximum number of seconds for a monitor to wait for a ping reply before it times out. The value must be less than the delay value.
- max\_retries (Required) Number of permissible ping failures before changing the member's status to INACTIVE. Must be a number between 1 and 10...
- url\_path (Optional) Required for HTTP(S) types. URI path that will be accessed if monitor type is HTTP or HTTPS.
- http\_method (Optional) Required for HTTP(S) types. The HTTP method used for requests by the monitor. If this attribute is not specified, it defaults to "GET".
- expected\_codes (Optional) Required for HTTP(S) types. Expected HTTP codes for a passing HTTP(S) monitor. You can either specify a single status like "200", or a range like "200-202".
- admin\_state\_up (Optional) The administrative state of the monitor. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the monitor.
- tenant\_id See Argument Reference above.
- type See Argument Reference above.
- delay See Argument Reference above.
- timeout See Argument Reference above.
- max\_retries See Argument Reference above.
- url\_path See Argument Reference above.
- http\_method See Argument Reference above.
- expected\_codes See Argument Reference above.
- admin\_state\_up See Argument Reference above.

# » openstack\_fw\_firewall\_v1

Manages a v1 firewall resource within OpenStack.

## » Example Usage

```
resource "openstack_fw_rule_v1" "rule_1" {
                 = "my-rule-1"
 name
 description
                = "drop TELNET traffic"
                = "deny"
 action
                 = "tcp"
 protocol
 destination_port = "23"
                 = "true"
  enabled
}
resource "openstack_fw_rule_v1" "rule_2" {
                 = "my-rule-2"
 name
                 = "drop NTP traffic"
 description
                 = "deny"
 action
 protocol
              = "udp"
 destination_port = "123"
                  = "false"
  enabled
}
resource "openstack_fw_policy_v1" "policy_1" {
 name = "my-policy"
 rules = ["${openstack_fw_rule_v1.rule_1.id}",
    "${openstack_fw_rule_v1.rule_2.id}",
```

```
]
}
resource "openstack_fw_firewall_v1" "firewall_1" {
   name = "my-firewall"
   policy_id = "${openstack_fw_policy_v1.policy_1.id}"
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the v1 networking client. A networking client is needed to create a firewall. If omitted, the region argument of the provider is used. Changing this creates a new firewall.
- policy\_id (Required) The policy resource id for the firewall. Changing this updates the policy\_id of an existing firewall.
- name (Optional) A name for the firewall. Changing this updates the name of an existing firewall.
- description (Required) A description for the firewall. Changing this updates the description of an existing firewall.
- admin\_state\_up (Optional) Administrative up/down status for the firewall (must be "true" or "false" if provided defaults to "true"). Changing this updates the admin\_state\_up of an existing firewall.
- tenant\_id (Optional) The owner of the floating IP. Required if admin
  wants to create a firewall for another tenant. Changing this creates a new
  firewall.
- associated\_routers (Optional) Router(s) to associate this firewall instance with. Must be a list of strings. Changing this updates the associated routers of an existing firewall. Conflicts with no\_routers.
- no\_routers (Optional) Should this firewall not be associated with any routers (must be "true" or "false" if provide defaults to "false"). Conflicts with associated\_routers.
- value\_specs (Optional) Map of additional options.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- policy\_id See Argument Reference above.

- name See Argument Reference above.
- description See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- tenant\_id See Argument Reference above.
- associated\_routers See Argument Reference above.
- no\_routers See Argument Reference above.

### » Import

Firewalls can be imported using the id, e.g.

\$ terraform import openstack\_fw\_firewall\_v1.firewall\_1 c9e39fb2-ce20-46c8-a964-25f3898c7a97

# » openstack\_fw\_policy\_v1

Manages a v1 firewall policy resource within OpenStack.

### » Example Usage

```
resource "openstack_fw_rule_v1" "rule_1" {
 name
                = "my-rule-1"
               = "drop TELNET traffic"
 description
                = "deny"
 action
            = "tcp"
 protocol
 destination_port = "23"
 enabled
            = "true"
}
resource "openstack_fw_rule_v1" "rule_2" {
         = "my-rule-2"
 name
 description = "drop NTP traffic"
               = "deny"
 action
               = "udp"
 protocol
 destination_port = "123"
 enabled = "false"
}
resource "openstack_fw_policy_v1" "policy_1" {
 name = "my-policy"
 rules = ["${openstack_fw_rule_v1.rule_1.id}",
   "${openstack_fw_rule_v1.rule_2.id}",
 ]
```

The following arguments are supported:

- region (Optional) The region in which to obtain the v1 networking client. A networking client is needed to create a firewall policy. If omitted, the region argument of the provider is used. Changing this creates a new firewall policy.
- name (Optional) A name for the firewall policy. Changing this updates the name of an existing firewall policy.
- description (Optional) A description for the firewall policy. Changing this updates the description of an existing firewall policy.
- rules (Optional) An array of one or more firewall rules that comprise the policy. Changing this results in adding/removing rules from the existing firewall policy.
- audited (Optional) Audit status of the firewall policy (must be "true" or "false" if provided defaults to "false"). This status is set to "false" whenever the firewall policy or any of its rules are changed. Changing this updates the audited status of an existing firewall policy.
- shared (Optional) Sharing status of the firewall policy (must be "true" or "false" if provided). If this is "true" the policy is visible to, and can be used in, firewalls in other tenants. Changing this updates the shared status of an existing firewall policy. Only administrative users can specify if the policy should be shared.
- value specs (Optional) Map of additional options.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- audited See Argument Reference above.
- shared See Argument Reference above.

#### » Import

Firewall Policies can be imported using the id, e.g.

# $ightsymbol{"} openstack_fw_rule_v1$

Manages a v1 firewall rule resource within OpenStack.

### » Example Usage

# » Argument Reference

- region (Optional) The region in which to obtain the v1 Compute client. A Compute client is needed to create a firewall rule. If omitted, the region argument of the provider is used. Changing this creates a new firewall rule.
- name (Optional) A unique name for the firewall rule. Changing this updates the name of an existing firewall rule.
- description (Optional) A description for the firewall rule. Changing this updates the description of an existing firewall rule.
- protocol (Required) The protocol type on which the firewall rule operates. Valid values are: tcp, udp, icmp, and any. Changing this updates the protocol of an existing firewall rule.
- action (Required) Action to be taken (must be "allow" or "deny") when the firewall rule matches. Changing this updates the action of an existing firewall rule.
- ip\_version (Optional) IP version, either 4 (default) or 6. Changing this updates the ip\_version of an existing firewall rule.
- source\_ip\_address (Optional) The source IP address on which the firewall rule operates. Changing this updates the source\_ip\_address of an existing firewall rule.

- destination\_ip\_address (Optional) The destination IP address on which the firewall rule operates. Changing this updates the destination\_ip\_address of an existing firewall rule.
- source\_port (Optional) The source port on which the firewall rule operates. Changing this updates the source\_port of an existing firewall rule.
- destination\_port (Optional) The destination port on which the firewall rule operates. Changing this updates the destination\_port of an existing firewall rule.
- enabled (Optional) Enabled status for the firewall rule (must be "true" or "false" if provided defaults to "true"). Changing this updates the enabled status of an existing firewall rule.
- tenant\_id (Optional) The owner of the firewall rule. Required if admin wants to create a firewall rule for another tenant. Changing this creates a new firewall rule.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- protocol See Argument Reference above.
- action See Argument Reference above.
- ip\_version See Argument Reference above.
- source\_ip\_address See Argument Reference above.
- destination\_ip\_address See Argument Reference above.
- source\_port See Argument Reference above.
- destination\_port See Argument Reference above.
- enabled See Argument Reference above.
- tenant\_id See Argument Reference above.

#### » Import

Firewall Rules can be imported using the id, e.g.

\$ terraform import openstack\_fw\_rule\_v1.rule\_1 8dbc0c28-e49c-463f-b712-5c5d1bbac327

# » openstack\_objectstorage\_container\_v1

Manages a V1 container resource within OpenStack.

## » Example Usage

```
resource "openstack_objectstorage_container_v1" "container_1" {
  region = "RegionOne"
  name = "tf-test-container-1"

metadata {
   test = "true"
  }
  content_type = "application/json"
}
```

## » Argument Reference

- region (Optional) The region in which to create the container. If omitted, the region argument of the provider is used. Changing this creates a new container.
- name (Required) A unique name for the container. Changing this creates a new container.
- container\_read (Optional) Sets an access control list (ACL) that grants read access. This header can contain a comma-delimited list of users that can read the container (allows the GET method for all objects in the container). Changing this updates the access control list read access.
- container\_sync\_to (Optional) The destination for container synchronization. Changing this updates container synchronization.
- container\_sync\_key (Optional) The secret key for container synchronization. Changing this updates container synchronization.
- container\_write (Optional) Sets an ACL that grants write access. Changing this updates the access control list write access.
- metadata (Optional) Custom key/value pairs to associate with the container. Changing this updates the existing container metadata.
- content\_type (Optional) The MIME type for the container. Changing this updates the MIME type.

• force\_destroy - (Optional, Default:false ) A boolean that indicates all objects should be deleted from the container so that the container can be destroyed without error. These objects are not recoverable.

### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- container\_read See Argument Reference above.
- container\_sync\_to See Argument Reference above.
- container\_sync\_key See Argument Reference above.
- container\_write See Argument Reference above.
- metadata See Argument Reference above.
- content\_type See Argument Reference above.

# » openstack objectstorage object v1

Manages a V1 container object resource within OpenStack.

# » Example Usage

#### » Example with simple content

```
resource "openstack_objectstorage_container_v1" "container_1" {
    region = "RegionOne"
    name = "tf-test-container-1"

metadata {
    test = "true"
    }

    content_type = "application/json"
}

resource "openstack_objectstorage_object_v1" "doc_1" {
    region = "RegionOne"
    container_name = "${openstack_objectstorage_container_v1.container_1.name}"
    name = "test/default.json"
    metadata {
        test = "true"
    }
}
```

```
content_type = "application/json"
  content = <<JSON
                "foo" : "bar"
JSON
}
» Example with content from file
resource "openstack_objectstorage_container_v1" "container_1" {
 region = "RegionOne"
 name
       = "tf-test-container-1"
 metadata {
   test = "true"
  content_type = "application/json"
resource "openstack_objectstorage_object_v1" "doc_1" {
 region
                = "RegionOne"
 container_name = "${openstack_objectstorage_container_v1.container_1.name}"
                = "test/default.json"
 metadata {
   test = "true"
 }
 content_type = "application/json"
  source
         = "./default.json"
}
```

# » Argument Reference

The following arguments are supported:

• container\_name - (Required) A unique (within an account) name for the container. The container name must be from 1 to 256 characters long and can start with any character and contain any pattern. Character set must be UTF-8. The container name cannot contain a slash (/) character because this character delimits the container and object name. For example,

- the path /v1/account/www/pages specifies the www container, not the www/pages container.
- content (Optional) A string representing the content of the object. Conflicts with source and copy\_from.
- content\_disposition (Optional) A string which specifies the override behavior for the browser. For example, this header might specify that the browser use a download program to save this file rather than show the file, which is the default.
- content\_encoding (Optional) A string representing the value of the Content-Encoding metadata.
- content\_type (Optional) A string which sets the MIME type for the object.
- copy\_from (Optional) A string representing the name of an object used to create the new object by copying the copy\_from object. The value is in form {container}/{object}. You must UTF-8-encode and then URL-encode the names of the container and object before you include them in the header. Conflicts with source and content.
- delete\_after (Optional) An integer representing the number of seconds
  after which the system removes the object. Internally, the Object Storage
  system stores this value in the X-Delete-At metadata item.
- delete\_at (Optional) An string representing the date when the system removes the object. For example, "2015-08-26" is equivalent to Mon, Wed, 26 Aug 2015 00:00:00 GMT.
- detect\_content\_type (Optional) If set to true, Object Storage guesses the content type based on the file extension and ignores the value sent in the Content-Type header, if present.
- etag (Optional) Used to trigger updates. The only meaningful value is \$\{md5(file("path/to/file"))\}.
- name (Required) A unique name for the object.
- object\_manifest (Optional) A string set to specify that this is a dynamic large object manifest object. The value is the container and object name prefix of the segment objects in the form container/prefix. You must UTF-8-encode and then URL-encode the names of the container and prefix before you include them in this header.
- region (Optional) The region in which to create the container. If omitted, the region argument of the provider is used. Changing this creates a new container.
- source (Optional) A string representing the local path of a file which will be used as the object's content. Conflicts with source and copy\_from.

The following attributes are exported:

- content\_length If the operation succeeds, this value is zero (0) or the length of informational or error text in the response body.
- content\_type If the operation succeeds, this value is the MIME type of the object. If the operation fails, this value is the MIME type of the error text in the response body.
- date The date and time the system responded to the request, using the preferred format of RFC 7231 as shown in this example Thu, 16 Jun 2016 15:10:38 GMT. The time is always in UTC.
- etag Whatever the value given in argument, will be overriden by the MD5 checksum of the uploaded object content. The value is not quoted. If it is an SLO, it would be MD5 checksum of the segments' etags.
- last\_modified The date and time when the object was last modified. The date and time stamp format is ISO 8601: CCYY-MM-DDThh:mm:ss±hh:mm For example, 2015-08-27T09:49:58-05:00. The ±hh:mm value, if included, is the time zone as an offset from UTC. In the previous example, the offset value is -05:00.
- static\_large\_object True if object is a multipart\_manifest.
- trans\_id A unique transaction ID for this request. Your service provider might need this value if you report a problem.
- container\_name See Argument Reference above.
- content See Argument Reference above.
- content\_disposition See Argument Reference above.
- content\_encoding See Argument Reference above.
- copy\_from See Argument Reference above.
- delete\_after See Argument Reference above.
- delete\_at See Argument Reference above.
- detect\_content\_type See Argument Reference above.
- name See Argument Reference above.
- object\_manifest See Argument Reference above.
- region See Argument Reference above.
- source See Argument Reference above.

# » openstack\_vpnaas\_ipsec\_policy\_v2

Manages a V2 Neutron IPSec policy resource within OpenStack.

## » Example Usage

```
resource "openstack_vpnaas_ipsec_policy_v2" "policy_1" {
  name = "my_policy"
}
```

# » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an IPSec policy. If omitted, the region argument of the provider is used. Changing this creates a new policy.
- name (Optional) The name of the policy. Changing this updates the name of the existing policy.
- tenant\_id (Optional) The owner of the policy. Required if admin wants to create a policy for another project. Changing this creates a new policy.
- description (Optional) The human-readable description for the policy. Changing this updates the description of the existing policy.
- auth\_algorithm (Optional) The authentication hash algorithm. Valid values are sha1, sha256, sha384, sha512. Default is sha1. Changing this updates the algorithm of the existing policy.
- encapsulation\_mode (Optional) The encapsulation mode. Valid values are tunnel and transport. Default is tunnel. Changing this updates the existing policy.
- encryption\_algorithm (Optional) The encryption algorithm. Valid values are 3des, aes-128, aes-192 and so on. The default value is aes-128. Changing this updates the existing policy.
- pfs (Optional) The perfect forward secrecy mode. Valid values are Group2, Group5 and Group14. Default is Group5. Changing this updates the existing policy.
- transform\_protocol (Optional) The transform protocol. Valid values are ESP, AH and AH-ESP. Changing this updates the existing policy. Default is ESP.

- lifetime (Optional) The lifetime of the security association. Consists of Unit and Value.
  - unit (Optional) The units for the lifetime of the security association.
     Can be either seconds or kilobytes. Default is seconds.
  - value (Optional) The value for the lifetime of the security association. Must be a positive integer. Default is 3600.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- description See Argument Reference above.
- auth\_algorithm See Argument Reference above.
- encapsulation\_mode See Argument Reference above.
- encryption\_algorithm See Argument Reference above.
- pfs See Argument Reference above.
- transform\_protocol See Argument Reference above.
- lifetime See Argument Reference above.
  - unit See Argument Reference above.
  - value See Argument Reference above.
- value\_specs See Argument Reference above.

#### » Import

Policies can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_ipsec\_policy\_v2.policy\_1 832cb7f3-59fe-40cf-8f64-8350ffc

# ${\bf »~openstack\_vpnaas\_ike\_policy\_v2}$

Manages a V2 Neutron IKE policy resource within OpenStack.

## » Example Usage

```
resource "openstack_vpnaas_ike_policy_v2" "policy_1" {
  name = "my_policy"
}
```

# » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VPN service. If omitted, the region argument of the provider is used. Changing this creates a new service.
- name (Optional) The name of the policy. Changing this updates the name of the existing policy.
- tenant\_id (Optional) The owner of the policy. Required if admin wants to create a service for another policy. Changing this creates a new policy.
- description (Optional) The human-readable description for the policy. Changing this updates the description of the existing policy.
- auth\_algorithm (Optional) The authentication hash algorithm. Valid values are sha1, sha256, sha384, sha512. Default is sha1. Changing this updates the algorithm of the existing policy.
- encryption\_algorithm (Optional) The encryption algorithm. Valid values are 3des, aes-128, aes-192 and so on. The default value is aes-128. Changing this updates the existing policy.
- pfs (Optional) The perfect forward secrecy mode. Valid values are Group2, Group5 and Group14. Default is Group5. Changing this updates the existing policy.
- phase1\_negotiation\_mode (Optional) The IKE mode. A valid value is main, which is the default. Changing this updates the existing policy.
- ike\_version (Optional) The IKE mode. A valid value is v1 or v2. Default is v1. Changing this updates the existing policy.
- lifetime (Optional) The lifetime of the security association. Consists of Unit and Value.
  - unit (Optional) The units for the lifetime of the security association.
     Can be either seconds or kilobytes. Default is seconds.
  - value (Optional) The value for the lifetime of the security association. Must be a positive integer. Default is 3600.
- value specs (Optional) Map of additional options.

#### » Attributes Reference

The following attributes are exported:

• region - See Argument Reference above.

- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- description See Argument Reference above.
- auth\_algorithm See Argument Reference above.
- encapsulation\_mode See Argument Reference above.
- encryption\_algorithm See Argument Reference above.
- pfs See Argument Reference above.
- transform\_protocol See Argument Reference above.
- lifetime See Argument Reference above.
  - unit See Argument Reference above.
  - value See Argument Reference above.
- value\_specs See Argument Reference above.

## » Import

Services can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_ike\_policy\_v2.policy\_1 832cb7f3-59fe-40cf-8f64-8350ffc03

# » openstack\_vpnaas\_service\_v2

Manages a V2 Neutron VPN service resource within OpenStack.

#### » Example Usage

```
resource "openstack_vpnaas_service_v2" "service_1" {
  name = "my_service"
  router_id = "14a75700-fc03-4602-9294-26ee44f366b3"
  admin_state_up = "true"
}
```

# » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VPN service. If omitted, the region argument of the provider is used. Changing this creates a new service.
- name (Optional) The name of the service. Changing this updates the name of the existing service.

- tenant\_id (Optional) The owner of the service. Required if admin wants to create a service for another project. Changing this creates a new service.
- description (Optional) The human-readable description for the service. Changing this updates the description of the existing service.
- admin\_state\_up (Optional) The administrative state of the resource. Can either be up(true) or down(false). Changing this updates the administrative state of the existing service.
- subnet\_id (Optional) SubnetID is the ID of the subnet. Default is null.
- router\_id (Required) The ID of the router. Changing this creates a new service.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- router\_id See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- subnet\_id See Argument Reference above.
- status Indicates whether IPsec VPN service is currently operational. Values are ACTIVE, DOWN, BUILD, ERROR, PENDING\_CREATE, PENDING\_UPDATE, or PENDING\_DELETE.
- external\_v6\_ip The read-only external (public) IPv6 address that is used for the VPN service.
- external\_v4\_ip The read-only external (public) IPv4 address that is used for the VPN service.
- description See Argument Reference above.
- value\_specs See Argument Reference above.

### » Import

Services can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_service\_v2.service\_1 832cb7f3-59fe-40cf-8f64-8350ffc032

# » openstack\_vpnaas\_endpoint\_group\_v2

Manages a V2 Neutron Endpoint Group resource within OpenStack.

# » Example Usage

# » Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an endpoint group. If omitted, the region argument of the provider is used. Changing this creates a new group.
- name (Optional) The name of the group. Changing this updates the name of the existing group.
- tenant\_id (Optional) The owner of the group. Required if admin wants to create an endpoint group for another project. Changing this creates a new group.
- description (Optional) The human-readable description for the group. Changing this updates the description of the existing group.
- type The type of the endpoints in the group. A valid value is subnet, cidr, network, router, or vlan. Changing this creates a new group.
- endpoints List of endpoints of the same type, for the endpoint group. The values will depend on the type. Changing this creates a new group.
- value\_specs (Optional) Map of additional options.

#### » Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant id See Argument Reference above.
- description See Argument Reference above.
- type See Argument Reference above.
- endpoints See Argument Reference above.
- value\_specs See Argument Reference above.

## » Import

Groups can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_endpoint\_group\_v2.group\_1 832cb7f3-59fe-40cf-8f64-8350f

# » openstack\_vpnaas\_site\_connection\_v2

Manages a V2 Neutron IPSec site connection resource within OpenStack.

## » Example Usage

```
resource "openstack_vpnaas_site_connection_v2" "conn_1" {
    name = "connection_1"
    ikepolicy_id = "${openstack_vpnaas_ike_policy_v2.policy_2.id}"
    ipsecpolicy_id = "${openstack_vpnaas_ipsec_policy_v2.policy_1.id}"
    vpnservice_id = "${openstack_vpnaas_service_v2.service_1.id}"
    psk = "secret"
    peer_address = "192.168.10.1"
    local_ep_group_id = "${openstack_vpnaas_endpoint_group_v2.group_2.id}"
    peer_ep_group_id = "${openstack_vpnaas_endpoint_group_v2.group_1.id}"
}
```

# » Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an IPSec site connection. If omitted, the region argument of the provider is used. Changing this creates a new site connection.
- name (Optional) The name of the connection. Changing this updates the name of the existing connection.
- tenant\_id (Optional) The owner of the connection. Required if admin
  wants to create a connection for another project. Changing this creates a
  new connection.
- description (Optional) The human-readable description for the connection. Changing this updates the description of the existing connection.
- admin\_state\_up (Optional) The administrative state of the resource. Can either be up(true) or down(false). Changing this updates the administrative state of the existing connection.

- ikepolicy\_id (Required) The ID of the IKE policy. Changing this creates a new connection.
- vpnservice\_id (Required) The ID of the VPN service. Changing this creates a new connection.
- local\_ep\_group\_id (Optional) The ID for the endpoint group that contains private subnets for the local side of the connection. You must specify this parameter with the peer\_ep\_group\_id parameter unless in backward-compatible mode where peer\_cidrs is provided with a subnet\_id for the VPN service. Changing this updates the existing connection.
- ipsecpolicy\_id (Required) The ID of the IPsec policy. Changing this creates a new connection.
- peer\_id (Required) The peer router identity for authentication. A valid value is an IPv4 address, IPv6 address, e-mail address, key ID, or FQDN. Typically, this value matches the peer\_address value. Changing this updates the existing policy.
- peer\_ep\_group\_id (Optional) The ID for the endpoint group that contains private CIDRs in the form < net\_address > / < prefix > for the peer side of the connection. You must specify this parameter with the local\_ep\_group\_id parameter unless in backward-compatible mode where peer cidrs is provided with a subnet id for the VPN service.
- local\_id (Optional) An ID to be used instead of the external IP address for a virtual router used in traffic between instances on different networks in east-west traffic. Most often, local ID would be domain name, email address, etc. If this is not configured then the external IP address will be used as the ID.
- peer\_address (Required) The peer gateway public IPv4 or IPv6 address or FQDN.
- psk (Required) The pre-shared key. A valid value is any string.
- initiator (Optional) A valid value is response-only or bi-directional.
   Default is bi-directional.
- peer\_cidrs (Optional) Unique list of valid peer private CIDRs in the form < net\_address > / < prefix > .
- dpd (Optional) A dictionary with dead peer detection (DPD) protocol controls.
  - action (Optional) The dead peer detection (DPD) action. A valid value is clear, hold, restart, disabled, or restart-by-peer. Default value is hold.
  - timeout (Optional) The dead peer detection (DPD) timeout in seconds. A valid value is a positive integer that is greater than the DPD interval value. Default is 120.

- interval (Optional) The dead peer detection (DPD) interval, in seconds. A valid value is a positive integer. Default is 30.
- mtu (Optional) The maximum transmission unit (MTU) value to address fragmentation. Minimum value is 68 for IPv4, and 1280 for IPv6.
- value\_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant\_id See Argument Reference above.
- admin\_state\_up See Argument Reference above.
- description See Argument Reference above.
- dpd See Argument Reference above.
- psk See Argument Reference above.
- initiator See Argument Reference above.
- peer\_address See Argument Reference above.
- peer\_id See Argument Reference above.
- peer\_cidrs See Argument Reference above.
- mtu See Argument Reference above.
- local\_id See Argument Reference above.
- peer\_ep\_group\_id See Argument Reference above.
- ipsecpolicy\_id See Argument Reference above.
- vpnservice\_id See Argument Reference above.
- ikepolicy\_id See Argument Reference above.
- value\_specs See Argument Reference above.

# » Import

Site Connections can be imported using the id, e.g.

\$ terraform import openstack\_vpnaas\_site\_connection\_v2.conn\_1 832cb7f3-59fe-40cf-8f64-8350f: