» panos_system_info

Use this data source to retrieve "show system info" from the NGFW or Panorama.

All contents of "show system info" are saved to the info variable. In addition, the version number of PAN-OS encountered is saved to multiple fields for ease of access.

» Example Usage

```
data "panos system info" "example" {}
```

» Attribute Reference

The following attributes are present:

- info a map containing the contents of show system info.
- version_major Major version number.
- version_minor Minor version number.
- version_patch Patch version number.

» panos_panorama_address_group

This resource allows you to add/update/delete Panorama address groups.

Address groups are either statically defined or dynamically defined, so only static_addresses or dynamic_match should be defined within a given address group.

» Example Usage

```
# Static group
resource "panos_panorama_address_group" "example1" {
    name = "static ntp grp"
    description = "My NTP servers"
    static_addresses = ["ntp1", "ntp2", "ntp3"]
}
# Dynamic group
resource "panos_panorama_address_group" "example2" {
    name = "dynamic grp"
    description = "My internal NTP servers"
```

```
dynamic_match = "'internal' and 'ntp'"
}
```

The following arguments are supported:

- name (Required) The address group's name.
- device_group (Optional) The device group to put the address group into (default: shared).
- static_addresses (Optional) The address objects to include in this statically defined address group.
- dynamic_match (Optional) The IP tags to include in this DAG.
- description (Optional) The address group's description.
- tags (Optional) List of administrative tags.

» panos panorama address object

This resource allows you to add/update/delete address objects on Panorama.

» Example Usage

```
resource "panos_panorama_address_object" "example" {
   name = "localnet"
   value = "192.168.80.0/24"
   description = "The 192.168.80 network"
   tags = ["internal", "dmz"]
}
```

» Argument Reference

- name (Required) The address object's name.
- device_group (Optional) The device group to put the address object into (default: shared).
- type (Optional) The type of address object. This can be ip-netmask (default), ip-range, or fqdn.
- value (Required) The address object's value. This can take various forms depending on what type of address object this is, but can be something like 192.168.80.150 or 192.168.80.0/24.
- description (Optional) The address object's description.

• tags - (Optional) List of administrative tags.

» panos_panorama_administrative_tag

This resource allows you to add/update/delete Panorama administrative tags.

» Example Usage

```
resource "panos_panorama_administrative_tag" "example" {
   name = "tag1"
   color = "color5"
   comment = "Internal resources"
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The administrative tag's name.
- device_group (Optional) The device group to put the administrative tag into (default: shared).
- color (Optional) The tag's color. This should be either an empty string (no color) or a string such as color1 or color15. Note that for maximum portability, you should limit color usage to color16, which was available in PAN-OS 6.1. PAN-OS 8.1's colors go up to color42. The value color18 is reserved internally by PAN-OS and thus not available for use.
- comment (Optional) The administrative tag's description.

» panos_panorama_device_group

This resource allows you to add/update/delete Panorama device groups.

This resource has some overlap with the panos_panorama_device_group_entry resource. If you want to use this resource with the other one, then make sure that your panos_panorama_device_group spec does not define any device blocks, and just stays as "computed".

This is the appropriate resource to use if terraform destroy should delete the device group.

» Example Usage

```
resource "panos_panorama_device_group" "example" {
   name = "my device group"
   description = "description here"
   device {
       serial = "00112233"
   }
   device {
       serial = "44556677"
       vsys_list = ["vsys1", "vsys2"]
   }
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The device group's name.
- description (Optional) The device group's description.
- device The device definition (see below).

The following arguments are valid for each device section:

- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos_panorama_device_group_entry

This resource allows you to add/update/delete a specific device in a Panorama device group.

This resource has some overlap with the panos_panorama_device_group resource. If you want to use this resource with the other one, then make sure that your panos_panorama_device_group spec does not define any device blocks, and just stays as "computed".

This is the appropriate resource to use if you have a pre-existing device group in Panorama and don't want Terraform to delete it on terraform destroy.

An interesting side effect of the underlying XML API - if the device group does not already exist, then this resource can actually create it. However, since only the single entry for the specific serial number is deleted, then a terraform destroy would not remove the device group itself in this situation.

» Example Usage

```
# Example for a virtual firewall.
resource "panos_panorama_device_group_entry" "example1" {
    device_group = "my device group"
    serial = "00112233"
}
# Example for a physical firewall with multi-vsys enabled.
resource "panos_panorama_device_group_entry" "example2" {
    device_group = "my device group"
    serial = "44556677"
    vsys_list = ["vsys1", "vsys2"]
}
```

» Argument Reference

The following arguments are supported:

- device_group (Required) The device group's name.
- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos_panorama_nat_rule

This resource allows you to add/update/delete Panorama NAT rules.

Note: panos panorama nat policy is known as panos panorama nat rule.

The prefix sat stands for "Source Address Translation" while the prefix "dat" stands for "Destination Address Translation". The order of the params in this resource and their naming matches how the params are presented in the GUI. Thus, having a GUI window open while creating your resource definition will simplify the process.

Note that while many of the params for this resource are optional in an absolute sense, depending on what type of NAT you wish to configure, certain params may become necessary to correctly configure the NAT rule.

» Example Usage

```
resource "panos panorama nat rule" "example" {
```

```
name = "my nat rule"
source_zones = ["zone1"]
destination_zone = "zone2"
to_interface = "ethernet1/3"
source_addresses = ["any"]
destination_addresses = ["any"]
sat_type = "none"
dat_type = "static"
dat_address = "my dat address object"
target {
    serial = "123456"
    vsys_list = ["vsys1", "vsys2"]
}
```

- name (Required) The NAT rule's name.
- device_group (Optional) The device group to put the NAT rule into (default: shared).
- rulebase (Optional) The rulebase. This can be pre-rulebase (default), post-rulebase, or rulebase.
- description (Optional) The description.
- type (Optional). NAT type. This can be ipv4 (default), nat64, or nptv6.
- source zones (Required) The list of source zone(s).
- destination_zone (Required) The destination zone.
- to_interface (Optional) Egress interface from route lookup (default: any).
- service (Optional) Service (default: any).
- source_addresses (Required) List of source address(es).
- destination_addresses (Required) List of destination address(es).
- sat_type (Optional) Type of source address translation. This can be none (default), dynamic-ip-and-port, dynamic-ip, or static-ip.
- sat_address_type (Optional) Source address translation address type.
- sat_translated_addresses (Optional) Source address translation list of translated addresses.
- sat_interface (Optional) Source address translation interface.
- sat_ip_address (Optional) Source address translation IP address.
- sat_fallback_type (Optional) Source address translation fallback type. This can be none, interface-address, or translated-address.
- sat_fallback_translated_addresses (Optional) Source address translation list of fallback translated addresses.

- sat_fallback_interface (Optional) Source address translation fall-back interface.
- sat_fallback_ip_type (Optional) Source address translation fallback IP type. This can be ip or floating.
- sat_fallback_ip_address (Optional) The source address translation fallback IP address.
- sat_static_translated_address (Optional) The statically translated source address.
- sat_static_bi_directional (Optional) Set to true to enable bi-directional source address translation.
- dat_type (Optional) Destination address translation type. This should be either static or dynamic. The dynamic option is only available on PAN-OS 8.1+.
- dat_address (Optional) Destination address translation's address. Requires dat type be set to "static" or "dynamic".
- dat_port (Optional) Destination address translation's port number. Requires dat_type be set to "static" or "dynamic".
- dat_dynamic_distribution (Optional, PAN-OS 8.1+) Distribution algorithm for destination address pool. The PAN-OS 8.1 GUI doesn't seem to set this anywhere, but this is added here for completeness' sake. Requires dat_type of "dynamic".
- disabled (Optional) Set to true to disable this rule.
- tags (Optional) List of administrative tags.
- target (Optional) A target definition (see below). If there are no target sections, then the rule will apply to every vsys of every device in the device group.
- negate_target (Optional, bool) Instead of applying the rule for the given serial numbers, apply it to everything except them.

The following arguments are valid for each target section:

- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos_panorama_nat_rule

This resource allows you to add/update/delete Panorama NAT rules.

Note: panos_panorama_nat_policy is known as panos_panorama_nat_rule.

The prefix sat stands for "Source Address Translation" while the prefix "dat" stands for "Destination Address Translation". The order of the params in this resource and their naming matches how the params are presented in the GUI.

Thus, having a GUI window open while creating your resource definition will simplify the process.

Note that while many of the params for this resource are optional in an absolute sense, depending on what type of NAT you wish to configure, certain params may become necessary to correctly configure the NAT rule.

» Example Usage

```
resource "panos_panorama_nat_rule" "example" {
   name = "my nat rule"
   source_zones = ["zone1"]
   destination_zone = "zone2"
   to_interface = "ethernet1/3"
   source_addresses = ["any"]
   destination_addresses = ["any"]
   sat_type = "none"
   dat_type = "static"
   dat_address = "my dat address object"
   target {
      serial = "123456"
      vsys_list = ["vsys1", "vsys2"]
   }
}
```

» Argument Reference

- name (Required) The NAT rule's name.
- device_group (Optional) The device group to put the NAT rule into (default: shared).
- rulebase (Optional) The rulebase. This can be pre-rulebase (default), post-rulebase, or rulebase.
- description (Optional) The description.
- type (Optional). NAT type. This can be ipv4 (default), nat64, or nptv6.
- source_zones (Required) The list of source zone(s).
- destination_zone (Required) The destination zone.
- to_interface (Optional) Egress interface from route lookup (default: any).
- service (Optional) Service (default: any).
- source_addresses (Required) List of source address(es).
- destination_addresses (Required) List of destination address(es).

- sat_type (Optional) Type of source address translation. This can be none (default), dynamic-ip-and-port, dynamic-ip, or static-ip.
- sat address type (Optional) Source address translation address type.
- sat_translated_addresses (Optional) Source address translation list of translated addresses.
- sat_interface (Optional) Source address translation interface.
- sat_ip_address (Optional) Source address translation IP address.
- sat_fallback_type (Optional) Source address translation fallback type. This can be none, interface-address, or translated-address.
- sat_fallback_translated_addresses (Optional) Source address translation list of fallback translated addresses.
- sat_fallback_interface (Optional) Source address translation fall-back interface.
- sat_fallback_ip_type (Optional) Source address translation fallback IP type. This can be ip or floating.
- sat_fallback_ip_address (Optional) The source address translation fallback IP address.
- sat_static_translated_address (Optional) The statically translated source address.
- sat_static_bi_directional (Optional) Set to true to enable bi-directional source address translation.
- dat_type (Optional) Destination address translation type. This should be either static or dynamic. The dynamic option is only available on PAN-OS 8.1+.
- dat_address (Optional) Destination address translation's address. Requires dat_type be set to "static" or "dynamic".
- dat_port (Optional) Destination address translation's port number. Requires dat_type be set to "static" or "dynamic".
- dat_dynamic_distribution (Optional, PAN-OS 8.1+) Distribution algorithm for destination address pool. The PAN-OS 8.1 GUI doesn't seem to set this anywhere, but this is added here for completeness' sake. Requires dat_type of "dynamic".
- disabled (Optional) Set to true to disable this rule.
- tags (Optional) List of administrative tags.
- target (Optional) A target definition (see below). If there are no target sections, then the rule will apply to every vsys of every device in the device group.
- negate_target (Optional, bool) Instead of applying the rule for the given serial numbers, apply it to everything except them.

The following arguments are valid for each target section:

- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos_panorama_security_policy

This resource allows you to manage the full security posture.

Note: panos_panorama_security_policies is known as panos_panorama_security_policy.

This resource manages the full set of security rules, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block. As this manages the full set of security rules for a given rulebase, any extraneous rules are removed on terraform apply.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url_filtering
- file_blocking
- wildfire_analysis
- data_filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

» Example Usage

```
resource "panos_panorama_security_policy" "example" {
   rule {
      name = "allow bizdev to dmz"
      source_zones = ["bizdev"]
      source_addresses = ["any"]
      source_users = ["any"]
      hip_profiles = ["any"]
      destination_zones = ["dmz"]
      destination_addresses = ["any"]
      applications = ["any"]
      services = ["application-default"]
      categories = ["any"]
      action = "allow"
```

```
}
    rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
        target {
            serial = "01234"
        target {
            serial = "56789"
            vsys_list = ["vsys1", "vsys3"]
        }
    }
}
```

The following arguments are supported:

- device_group (Optional) The device group to put the security policy into (default: shared).
- rulebase (Optional) The rulebase. This can be pre-rulebase (default), post-rulebase, or rulebase.
- rule The security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source_zones (Required) List of source zones.
- source_addresses (Required) List of source addresses.
- negate_source (Optional, bool) If the source should be negated.
- source_users (Required) List of source users.
- hip profiles (Required) List of HIP profiles.

- destination_zones (Required) List of destination zones.
- destination_addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log_setting (Optional) Log forwarding profile.
- log_start (Optional, bool) Log the start of the traffic flow.
- log_end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security rule schedule.
- icmp_unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware setting.
- vulnerability (Optional) Profile Setting: Profiles The Vulnerability Protection setting.
- url_filtering (Optional) Profile Setting: Profiles The URL filtering setting.
- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.
- target (Optional) A target definition (see below). If there are no target sections, then the rule will apply to every vsys of every device in the device group.
- negate_target (Optional, bool) Instead of applying the rule for the given serial numbers, apply it to everything except them.

The following arguments are valid for each target section:

- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos_panorama_security_policy

This resource allows you to manage the full security posture.

Note: panos_panorama_security_policies is known as panos_panorama_security_policy.

This resource manages the full set of security rules, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block. As this manages the full set of security rules for a given rulebase, any extraneous rules are removed on terraform apply.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url_filtering
- file_blocking
- wildfire_analysis
- data_filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

» Example Usage

```
resource "panos_panorama_security_policy" "example" {
   rule {
      name = "allow bizdev to dmz"
      source_zones = ["bizdev"]
      source_addresses = ["any"]
      source_users = ["any"]
      hip_profiles = ["any"]
      destination_zones = ["dmz"]
      destination_addresses = ["any"]
      applications = ["any"]
      services = ["application-default"]
      categories = ["any"]
      action = "allow"
```

```
}
    rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
        target {
            serial = "01234"
        target {
            serial = "56789"
            vsys_list = ["vsys1", "vsys3"]
        }
    }
}
```

The following arguments are supported:

- device_group (Optional) The device group to put the security policy into (default: shared).
- rulebase (Optional) The rulebase. This can be pre-rulebase (default), post-rulebase, or rulebase.
- rule The security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source_zones (Required) List of source zones.
- source_addresses (Required) List of source addresses.
- negate_source (Optional, bool) If the source should be negated.
- source_users (Required) List of source users.
- hip_profiles (Required) List of HIP profiles.

- destination_zones (Required) List of destination zones.
- destination_addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log_setting (Optional) Log forwarding profile.
- log_start (Optional, bool) Log the start of the traffic flow.
- log_end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security rule schedule.
- icmp_unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware setting.
- vulnerability (Optional) Profile Setting: Profiles The Vulnerability Protection setting.
- url_filtering (Optional) Profile Setting: Profiles The URL filtering setting.
- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.
- target (Optional) A target definition (see below). If there are no target sections, then the rule will apply to every vsys of every device in the device group.
- negate_target (Optional, bool) Instead of applying the rule for the given serial numbers, apply it to everything except them.

The following arguments are valid for each target section:

- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos_panorama_security_rule_group

This resource allows you to add/update/delete Panorama security rule groups.

Note: panos_panorama_security_policy_group is known as panos_panorama_security_rule_group.

This resource manages clusters of security rules in a single device group, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block.

Because this resource only manages what it's told to, it will not manage any rules that may already exist on Panorama. This has implications on the effective security posture of Panorama, but it will allow you to spread your security rules across multiple Terraform state files. If you want to verify that the security rules are only what appears in the plan file, then you should probably be using the panos_panorama_security_policy resource.

Although you cannot modify non-group security rules with this resource, the position_keyword and position_reference parameters allow you to reference some other security rule that already exists, using it as a means to ensure some rough placement within the ruleset as a whole.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url filtering
- file blocking
- wildfire_analysis
- data filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

» Best Practices

As is to be expected, if you are separating your deployment across multiple plan files, make sure that at most only one plan specifies any given absolute positioning keyword such as "top" or "directly below", otherwise they'll keep shoving each other out of the way indefinitely.

Best practices are to specify one group as top (if you need it), one group as bottom (this is where you have your logging deny rule), then all other groups should be above the first rule of the bottom group. You do it this way because rules will natually be added at the tail end of the rulebase, so they will always be after the first group, but what you want is for them to be before the last group's rules.

» Example Usage

```
resource "panos panorama security rule group" "example" {
    position_keyword = "above"
    position reference = "deny everything else"
    rule {
        name = "allow bizdev to dmz"
        source_zones = ["bizdev"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["dmz"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "allow"
    }
    rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
        target {
            serial = "01234"
        }
        target {
            serial = "56789"
```

```
vsys_list = ["vsys1", "vsys3"]
}
}
```

The following arguments are supported:

- device_group (Optional) The device group to put the security rules into (default: shared).
- rulebase (Optional) The rulebase. This can be pre-rulebase (default), post-rulebase, or rulebase.
- position_keyword (Optional) A positioning keyword for this group. This can be before, directly before, after, directly after, top, bottom, or left empty (the default) to have no particular placement. This param works in combination with the position_reference param.
- position_reference (Optional) Required if position_keyword is one of the "above" or "below" variants, this is the name of a non-group rule to use as a reference to place this group.
- rule The security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source zones (Required) List of source zones.
- source_addresses (Required) List of source addresses.
- negate_source (Optional, bool) If the source should be negated.
- source_users (Required) List of source users.
- hip profiles (Required) List of HIP profiles.
- destination_zones (Required) List of destination zones.
- destination_addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log setting (Optional) Log forwarding profile.
- log start (Optional, bool) Log the start of the traffic flow.

- log_end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security rule schedule.
- icmp_unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware setting.
- vulnerability (Optional) Profile Setting: Profiles The Vulnerability Protection setting.
- url_filtering (Optional) Profile Setting: Profiles The URL filtering setting.
- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.
- target (Optional) A target definition (see below). If there are no target sections, then the rule will apply to every vsys of every device in the device group.
- negate_target (Optional, bool) Instead of applying the rule for the given serial numbers, apply it to everything except them.

The following arguments are valid for each target section:

- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos_panorama_security_rule_group

This resource allows you to add/update/delete Panorama security rule groups.

Note: panos_panorama_security_policy_group is known as panos_panorama_security_rule_group.

This resource manages clusters of security rules in a single device group, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block.

Because this resource only manages what it's told to, it will not manage any rules that may already exist on Panorama. This has implications on the effective security posture of Panorama, but it will allow you to spread your security rules

across multiple Terraform state files. If you want to verify that the security rules are only what appears in the plan file, then you should probably be using the panos_panorama_security_policy resource.

Although you cannot modify non-group security rules with this resource, the position_keyword and position_reference parameters allow you to reference some other security rule that already exists, using it as a means to ensure some rough placement within the ruleset as a whole.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url_filtering
- file_blocking
- wildfire_analysis
- data_filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

» Best Practices

As is to be expected, if you are separating your deployment across multiple plan files, make sure that at most only one plan specifies any given absolute positioning keyword such as "top" or "directly below", otherwise they'll keep shoving each other out of the way indefinitely.

Best practices are to specify one group as top (if you need it), one group as bottom (this is where you have your logging deny rule), then all other groups should be above the first rule of the bottom group. You do it this way because rules will natually be added at the tail end of the rulebase, so they will always be after the first group, but what you want is for them to be before the last group's rules.

» Example Usage

```
resource "panos_panorama_security_rule_group" "example" {
    position_keyword = "above"
   position_reference = "deny everything else"
   rule {
        name = "allow bizdev to dmz"
        source zones = ["bizdev"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["dmz"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "allow"
    }
   rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
        target {
            serial = "01234"
        target {
            serial = "56789"
            vsys_list = ["vsys1", "vsys3"]
    }
}
```

» Argument Reference

The following arguments are supported:

• device_group - (Optional) The device group to put the security rules into

- (default: shared).
- rulebase (Optional) The rulebase. This can be pre-rulebase (default), post-rulebase, or rulebase.
- position_keyword (Optional) A positioning keyword for this group. This can be before, directly before, after, directly after, top, bottom, or left empty (the default) to have no particular placement. This param works in combination with the position_reference param.
- position_reference (Optional) Required if position_keyword is one of the "above" or "below" variants, this is the name of a non-group rule to use as a reference to place this group.
- rule The security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source_zones (Required) List of source zones.
- source_addresses (Required) List of source addresses.
- negate source (Optional, bool) If the source should be negated.
- source_users (Required) List of source users.
- hip_profiles (Required) List of HIP profiles.
- destination_zones (Required) List of destination zones.
- destination addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log_setting (Optional) Log forwarding profile.
- log_start (Optional, bool) Log the start of the traffic flow.
- log_end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security rule schedule.
- icmp unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware setting.
- vulnerability (Optional) Profile Setting: Profiles The Vulnerability

Protection setting.

- url_filtering (Optional) Profile Setting: Profiles The URL filtering setting.
- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.
- target (Optional) A target definition (see below). If there are no target sections, then the rule will apply to every vsys of every device in the device group.
- negate_target (Optional, bool) Instead of applying the rule for the given serial numbers, apply it to everything except them.

The following arguments are valid for each target section:

- serial (Required) The serial number of the firewall.
- vsys_list (Optional) A subset of all available vsys on the firewall that should be in this device group. If the firewall is a virtual firewall, then this parameter should just be omitted.

» panos panorama service group

This resource allows you to add/update/delete Panorama service groups.

» Example Usage

```
resource "panos_panorama_service_group" "example" {
   name = "static ntp grp"
   services = ["svc1", "svc2"]
}
```

» Argument Reference

- name (Required) The service group's name.
- device_group (Optional) The device group to put the service group into (default: shared).
- services (Required) List of services to put in this service group.
- tags (Optional) List of administrative tags.

» panos_panorama_service_object

This resource allows you to add/update/delete Panorama service objects.

» Example Usage

```
resource "panos_panorama_service_object" "example" {
   name = "my_service"
   protocol = "tcp"
   description = "My service object"
   source_port = "2000-2049,2051-2099"
   destination_port = "32123"
   tags = ["internal", "dmz"]
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The service object's name.
- device_group (Optional) The device group to put the service object into (default: shared).
- description (Optional) The service object's description.
- protocol (Required) The service's protocol. This should be tcp or udp.
- source_port (Optional) The source port. This can be a single port number, range (1-65535), or comma separated (80,8080,443).
- destination_port (Required) The destination port. This can be a single port number, range (1-65535), or comma separated (80,8080,443).
- tags (Optional) List of administrative tags.

» panos_address_group

This resource allows you to add/update/delete address groups.

Address groups are either statically defined or dynamically defined, so only static_addresses or dynamic_match should be defined within a given address group.

» Example Usage

```
# Static group
resource "panos_address_group" "example1" {
```

```
name = "static ntp grp"
  description = "My NTP servers"
  static_addresses = ["ntp1", "ntp2", "ntp3"]
}

# Dynamic group
resource "panos_address_group" "example2" {
  name = "dynamic grp"
  description = "My internal NTP servers"
  dynamic_match = "'internal' and 'ntp'"
}
```

The following arguments are supported:

- name (Required) The address group's name.
- vsys (Optional) The vsys to put the address group into (default: vsys1).
- static_addresses (Optional) The address objects to include in this statically defined address group.
- dynamic_match (Optional) The IP tags to include in this DAG.
- description (Optional) The address group's description.
- tags (Optional) List of administrative tags.

» panos_address_object

This resource allows you to add/update/delete address objects.

» Example Usage

```
resource "panos_address_object" "example" {
   name = "localnet"
   value = "192.168.80.0/24"
   description = "The 192.168.80 network"
   tags = ["internal", "dmz"]
}
```

» Argument Reference

The following arguments are supported:

• name - (Required) The address object's name.

- vsys (Optional) The vsys to put the address object into (default: vsys1).
- type (Optional) The type of address object. This can be ip-netmask (default), ip-range, or fqdn.
- value (Required) The address object's value. This can take various forms depending on what type of address object this is, but can be something like 192.168.80.150 or 192.168.80.0/24.
- description (Optional) The address object's description.
- tags (Optional) List of administrative tags.

» panos_administrative_tag

This resource allows you to add/update/delete administrative tags.

» Example Usage

```
resource "panos_administrative_tag" "example" {
   name = "tag1"
   vsys = "vsys2"
   color = "color5"
   comment = "Internal resources"
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The administrative tag's name.
- vsys (Optional) The vsys to put the administrative tag into (default: vsys1).
- color (Optional) The tag's color. This should be either an empty string (no color) or a string such as color1 or color15. Note that for maximum portability, you should limit color usage to color16, which was available in PAN-OS 6.1. PAN-OS 8.1's colors go up to color42. The value color18 is reserved internally by PAN-OS and thus not available for use.
- comment (Optional) The administrative tag's description.

» panos_dag_tags

This resource allows you to add and remove dynamic address group tags.

The ip field should be unique in the panos_dag_tags block, and there should only be one panos_dag_tags block defined in a given plan.

Note - Tags are only removed during terraform destroy. Updating an applied terraform plan to have alternative tags will leave behind the old tags from the previously published plan(s).

» Example Usage

```
resource "panos_dag_tags" "example" {
    vsys = "vsys1"
    register {
        ip = "10.1.1.1"
        tags = ["tag1", "tag2"]
    }
    register {
        ip = "10.1.1.2"
        tags = ["tag3"]
    }
}
```

» Argument Reference

The following arguments are supported:

- vsys (Optional) The vsys to put the DAG tags in (default: vsys1).
- register (Required) A set that includes ip, the IP address to be tagged and tags, a list of tags to associate with the given IP.

» panos_ethernet_interface

This resource allows you to add/update/delete ethernet interfaces.

» Example Usage

```
# Configure a bare-bones ethernet interface.
resource "panos_ethernet_interface" "example1" {
    name = "ethernet1/3"
    vsys = "vsys1"
    mode = "layer3"
    static_ips = ["10.1.1.1/24"]
    comment = "Configured for internal traffic"
}
```

Configure a DHCP ethernet interface for vsys1 to use.

```
resource "panos_ethernet_interface" "example2" {
   name = "ethernet1/4"
   vsys = "vsys1"
   mode = "layer3"
   enable_dhcp = true
   create_dhcp_default_route = true
   dhcp_default_route_metric = 10
}
```

- name (Required) The ethernet interface's name. This should be something like ethernet1/X.
- vsys (Required) The vsys that will use this interface. This should be something like vsys1 or vsys3.
- mode (Required) The interface mode. This can be any of the following values: layer3, layer2, virtual-wire, tap, ha, decrypt-mirror, or aggregate-group.
- static_ips (Optional) List of static IPv4 addresses to set for this data interface.
- enable_dhcp (Optional) Set to true to enable DHCP on this interface.
- create_dhcp_default_route (Optional) Set to true to create a DHCP default route.
- dhcp_default_route_metric (Optional) The metric for the DHCP default route.
- ipv6 enabled (Optional) Set to true to enable IPv6.
- management_profile (Optional) The management profile.
- mtu (Optional) The MTU.
- adjust_tcp_mss (Optional) Adjust TCP MSS (default: false).
- netflow_profile (Optional) The netflow profile.
- lldp_enabled (Optional) Enable LLDP (default: false).
- lldp_profile (Optional) LLDP profile.
- link_speed (Optional) Link speed. This can be any of the following: 10, 100, 1000, or auto.
- link_duplex (Optional) Link duplex setting. This can be full, half, or auto.
- link_state (Optional) The link state. This can be up, down, or auto.
- aggregate_group (Optional) The aggregate group (applicable for physical firewalls only).
- comment (Optional) The interface comment.
- ipv4_mss_adjust (Optional, PAN-OS 8.0+) The IPv4 MSS adjust value.
- ipv6 mss adjust (Optional, PAN-OS 8.0+) The IPv6 MSS adjust value.

» panos_general_settings

This resource allows you to update the general device settings, such as DNS or the hostname.

All params are optional for this resource. If any options are not specified, then whatever is already configured on the firewall is left as-is. The general device settings will always exist on the firewall, so terraform destroy does not remove config from the firewall.

» Example Usage

```
resource "panos_general_settings" "example" {
   hostname = "ngfw220"
   dns_primary = "10.5.1.10"
   ntp_primary = "10.5.1.10"
   ntp_primary_auth_type = "none"
}
```

» Argument Reference

- hostname Firewall hostname.
- timezone The timezone (e.g. US/Pacific).
- domain The domain.
- update_server The update server (Default: updates.paloaltonetworks.com).
- verify_update_server Verify update server identity (Default: true).
- dns_primary Primary DNS server.
- dns_secondary Secondary DNS server.
- ntp primary address Primary NTP server.
- ntp_primary_auth_type Primary NTP auth type. This can be none, autokey, or symmetric-key.
- ntp_primary_key_id Primary NTP symmetric-key key ID.
- ntp_primary_algorithm Primary NTP symmetric-key algorithm. This
 can be sha1 or md5.
- ntp_primary_auth_key Primary NTP symmetric-key auth key. This is the SHA1 hash if the algorithm is sha1, or the md5sum if the algorithm is md5.
- ntp_secondary_address Secondary NTP server.
- ntp_secondary_auth_type Secondary NTP auth type. This can be none, autokey, or symmetric-key.
- ntp_secondary_key_id Secondary NTP symmetric-key key ID.
- ntp_secondary_algorithm Secondary NTP symmetric-key algorithm.
 This can be sha1 or md5.

• ntp_secondary_auth_key - Secondary NTP symmetric-key auth key. This is the SHA1 hash if the algorithm is sha1, or the md5sum if the algorithm is md5.

» panos management profile

This resource allows you to add/update/delete interface management profiles.

» Example Usage

```
resource "panos_management_profile" "example" {
   name = "allow ping"
   ping = true
   permitted_ips = ["10.1.1.0/24", "192.168.80.0/24"]
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The management profile's name.
- ping (Optional) Allow ping.
- telnet (Optional) Allow telnet.
- ssh (Optional) Allow SSH.
- http (Optional) Allow HTTP.
- http_ocsp (Optional) Allow HTTP OCSP.
- https (Optional) Allow HTTPS.
- snmp (Optional) Allow SNMP.
- response_pages (Optional) Allow response pages.
- userid_service (Optional) Allow User ID service.
- userid_syslog_listener_ssl (Optional) Allow User ID syslog listener for SSL.
- userid_syslog_listener_udp (Optional) Allow User ID syslog listener for UDP.
- permitted_ips (Optional) The list of permitted IP addresses or address ranges for this management profile.

» panos_nat_rule

This resource allows you to add/update/delete NAT rules.

Note: panos_nat_policy is known as panos_nat_rule.

The prefix sat stands for "Source Address Translation" while the prefix "dat" stands for "Destination Address Translation". The order of the params in this resource and their naming matches how the params are presented in the GUI. Thus, having a GUI window open while creating your resource definition will simplify the process.

Note that while many of the params for this resource are optional in an absolute sense, depending on what type of NAT you wish to configure, certain params may become necessary to correctly configure the NAT rule.

» Example Usage

```
resource "panos_nat_rule" "example" {
   name = "my nat rule"
   source_zones = ["zone1"]
   destination_zone = "zone2"
   to_interface = "ethernet1/3"
   source_addresses = ["any"]
   destination_addresses = ["any"]
   sat_type = "none"
   dat_type = "static"
   dat_address = "my dat address object"
}
```

» Argument Reference

- name (Required) The NAT rule's name.
- vsys (Optional) The vsys to put the NAT rule into (default: vsys1).
- rulebase (Optional, Deprecated) The rulebase. For firewalls, there is only the rulebase value (default), but on Panorama, there is also pre-rulebase and post-rulebase.
- description (Optional) The description.
- type (Optional). NAT type. This can be ipv4 (default), nat64, or nptv6.
- source_zones (Required) The list of source zone(s).
- destination_zone (Required) The destination zone.
- to_interface (Optional) Egress interface from route lookup (default: any).
- service (Optional) Service (default: any).
- source_addresses (Required) List of source address(es).
- destination_addresses (Required) List of destination address(es).
- sat_type (Optional) Type of source address translation. This can be none (default), dynamic-ip-and-port, dynamic-ip, or static-ip.

- sat_address_type (Optional) Source address translation address type.
- sat_translated_addresses (Optional) Source address translation list of translated addresses.
- sat_interface (Optional) Source address translation interface.
- sat_ip_address (Optional) Source address translation IP address.
- sat_fallback_type (Optional) Source address translation fallback type. This can be none, interface-address, or translated-address.
- sat_fallback_translated_addresses (Optional) Source address translation list of fallback translated addresses.
- sat_fallback_interface (Optional) Source address translation fallback interface.
- sat_fallback_ip_type (Optional) Source address translation fallback IP type. This can be ip or floating.
- sat_fallback_ip_address (Optional) The source address translation fallback IP address.
- sat_static_translated_address (Optional) The statically translated source address.
- sat_static_bi_directional (Optional) Set to true to enable bi-directional source address translation.
- dat_type (Optional) Destination address translation type. This should be either static or dynamic. The dynamic option is only available on PAN-OS 8.1+.
- dat_address (Optional) Destination address translation's address. Requires dat_type be set to "static" or "dynamic".
- dat_port (Optional) Destination address translation's port number. Requires dat type be set to "static" or "dynamic".
- dat_dynamic_distribution (Optional, PAN-OS 8.1+) Distribution algorithm for destination address pool. The PAN-OS 8.1 GUI doesn't seem to set this anywhere, but this is added here for completeness' sake. Requires dat_type of "dynamic".
- disabled (Optional) Set to true to disable this rule.
- tags (Optional) List of administrative tags.

» panos_nat_rule

This resource allows you to add/update/delete NAT rules.

Note: panos_nat_policy is known as panos_nat_rule.

The prefix sat stands for "Source Address Translation" while the prefix "dat" stands for "Destination Address Translation". The order of the params in this resource and their naming matches how the params are presented in the GUI. Thus, having a GUI window open while creating your resource definition will simplify the process.

Note that while many of the params for this resource are optional in an absolute sense, depending on what type of NAT you wish to configure, certain params may become necessary to correctly configure the NAT rule.

» Example Usage

```
resource "panos_nat_rule" "example" {
   name = "my nat rule"
   source_zones = ["zone1"]
   destination_zone = "zone2"
   to_interface = "ethernet1/3"
   source_addresses = ["any"]
   destination_addresses = ["any"]
   sat_type = "none"
   dat_type = "static"
   dat_address = "my dat address object"
}
```

» Argument Reference

- name (Required) The NAT rule's name.
- vsys (Optional) The vsys to put the NAT rule into (default: vsys1).
- rulebase (Optional, Deprecated) The rulebase. For firewalls, there is only the rulebase value (default), but on Panorama, there is also pre-rulebase and post-rulebase.
- description (Optional) The description.
- type (Optional). NAT type. This can be ipv4 (default), nat64, or nptv6.
- source_zones (Required) The list of source zone(s).
- destination_zone (Required) The destination zone.
- to_interface (Optional) Egress interface from route lookup (default: any).
- service (Optional) Service (default: any).
- source_addresses (Required) List of source address(es).
- destination_addresses (Required) List of destination address(es).
- sat_type (Optional) Type of source address translation. This can be none (default), dynamic-ip-and-port, dynamic-ip, or static-ip.
- sat_address_type (Optional) Source address translation address type.
- sat_translated_addresses (Optional) Source address translation list of translated addresses.
- sat_interface (Optional) Source address translation interface.
- sat_ip_address (Optional) Source address translation IP address.

- sat_fallback_type (Optional) Source address translation fallback type. This can be none, interface-address, or translated-address.
- sat_fallback_translated_addresses (Optional) Source address translation list of fallback translated addresses.
- sat_fallback_interface (Optional) Source address translation fallback interface.
- sat_fallback_ip_type (Optional) Source address translation fallback IP type. This can be ip or floating.
- sat_fallback_ip_address (Optional) The source address translation fallback IP address.
- sat_static_translated_address (Optional) The statically translated source address.
- sat_static_bi_directional (Optional) Set to true to enable bi-directional source address translation.
- dat_type (Optional) Destination address translation type. This should be either static or dynamic. The dynamic option is only available on PAN-OS 8.1+.
- dat_address (Optional) Destination address translation's address. Requires dat_type be set to "static" or "dynamic".
- dat_port (Optional) Destination address translation's port number. Requires dat_type be set to "static" or "dynamic".
- dat_dynamic_distribution (Optional, PAN-OS 8.1+) Distribution algorithm for destination address pool. The PAN-OS 8.1 GUI doesn't seem to set this anywhere, but this is added here for completeness' sake. Requires dat_type of "dynamic".
- disabled (Optional) Set to true to disable this rule.
- tags (Optional) List of administrative tags.

» panos_security_policy

This resource allows you to manage the full security posture.

Note: panos_security_policies is known as panos_security_policy.

This resource manages the full set of security rules in a vsys, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group

param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url_filtering
- file_blocking
- wildfire analysis
- data_filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

» Example Usage

```
resource "panos_security_policy" "example" {
    rule {
        name = "allow bizdev to dmz"
        source_zones = ["bizdev"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["dmz"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "allow"
    }
   rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
    }
}
```

The following arguments are supported:

- vsys (Optional) The vsys to put the security policy into (default: vsys1).
- rulebase (Optional, Deprecated) The rulebase. For firewalls, there is only the rulebase value (default), but on Panorama, there is also pre-rulebase and post-rulebase.
- rule A security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source_zones (Required) List of source zones.
- source_addresses (Required) List of source addresses.
- negate source (Optional, bool) If the source should be negated.
- source_users (Required) List of source users.
- hip profiles (Required) List of HIP profiles.
- destination_zones (Required) List of destination zones.
- destination_addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log_setting (Optional) Log forwarding profile.
- log_start (Optional, bool) Log the start of the traffic flow.
- log_end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security policy schedule.
- icmp_unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware setting.
- vulnerability (Optional) Profile Setting: Profiles The Vulnerability Protection setting.
- url_filtering (Optional) Profile Setting: Profiles The URL filtering

setting.

- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.

» panos_security_policy

This resource allows you to manage the full security posture.

Note: panos_security_policies is known as panos_security_policy.

This resource manages the full set of security rules in a vsys, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url_filtering
- file_blocking
- wildfire_analysis
- data_filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

```
resource "panos_security_policy" "example" {
   rule {
     name = "allow bizdev to dmz"
     source_zones = ["bizdev"]
     source_addresses = ["any"]
```

```
source_users = ["any"]
        hip_profiles = ["any"]
        destination zones = ["dmz"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "allow"
    }
    rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source_addresses = ["any"]
        source users = ["any"]
        hip_profiles = ["any"]
        destination zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
    }
}
```

The following arguments are supported:

- vsys (Optional) The vsys to put the security policy into (default: vsys1).
- rulebase (Optional, Deprecated) The rulebase. For firewalls, there is only the rulebase value (default), but on Panorama, there is also pre-rulebase and post-rulebase.
- rule A security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source_zones (Required) List of source zones.
- source_addresses (Required) List of source addresses.
- negate_source (Optional, bool) If the source should be negated.
- source users (Required) List of source users.

- hip_profiles (Required) List of HIP profiles.
- destination_zones (Required) List of destination zones.
- destination addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log_setting (Optional) Log forwarding profile.
- log_start (Optional, bool) Log the start of the traffic flow.
- log_end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security policy schedule.
- icmp_unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware setting.
- vulnerability (Optional) Profile Setting: Profiles The Vulnerability Protection setting.
- url_filtering (Optional) Profile Setting: Profiles The URL filtering setting.
- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.

» panos_security_rule_group

This resource allows you to add/update/delete security rule groups.

Note: panos_security_policy_group is known as panos_security_rule_group.

This resource manages clusters of security rules in a single vsys, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block.

Because this resource only manages what it's told to, it will not manage any rules that may already exist on the firewall. This has implications on the effective

security posture of your firewall, but it will allow you to spread your security rules across multiple Terraform state files. If you want to verify that the security rules are only what appears in the plan file, then you should probably be using the panos_security_policy resource.

Although you cannot modify non-group security rules with this resource, the position_keyword and position_reference parameters allow you to reference some other security rule that already exists, using it as a means to ensure some rough placement within the ruleset as a whole.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url_filtering
- file_blocking
- wildfire_analysis
- data_filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

» Best Practices

As is to be expected, if you are separating your deployment across multiple plan files, make sure that at most only one plan specifies any given absolute positioning keyword such as "top" or "directly below", otherwise they'll keep shoving each other out of the way indefinitely.

Best practices are to specify one group as top (if you need it), one group as bottom (this is where you have your logging deny rule), then all other groups should be above the first rule of the bottom group. You do it this way because rules will natually be added at the tail end of the rulebase, so they will always be after the first group, but what you want is for them to be before the last group's rules.

» Example Usage

```
resource "panos_security_rule_group" "example" {
    position_keyword = "above"
   position_reference = "deny everything else"
    rule {
        name = "allow bizdev to dmz"
        source zones = ["bizdev"]
        source_addresses = ["any"]
        source users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["dmz"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "allow"
    }
   rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
}
```

» Argument Reference

The following arguments are supported:

- vsys (Optional) The vsys to put the security rule into (default: vsys1).
- position_keyword (Optional) A positioning keyword for this group. This can be before, directly before, after, directly after, top, bottom, or left empty (the default) to have no particular placement. This param works in combination with the position_reference param.
- position_reference (Optional) Required if position_keyword is one of the "above" or "below" variants, this is the name of a non-group rule to use as a reference to place this group.

• rule - The security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source zones (Required) List of source zones.
- source addresses (Required) List of source addresses.
- negate_source (Optional, bool) If the source should be negated.
- source_users (Required) List of source users.
- hip_profiles (Required) List of HIP profiles.
- destination_zones (Required) List of destination zones.
- destination_addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log_setting (Optional) Log forwarding profile.
- log_start (Optional, bool) Log the start of the traffic flow.
- log end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security rule schedule.
- icmp_unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware setting.
- vulnerability (Optional) Profile Setting: Profiles The Vulnerability Protection setting.
- $url_filtering (Optional)$ Profile Setting: Profiles The URL filtering setting.
- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.

» panos_security_rule_group

This resource allows you to add/update/delete security rule groups.

Note: panos_security_policy_group is known as panos_security_rule_group.

This resource manages clusters of security rules in a single vsys, enforcing both the contents of individual rules as well as their ordering. Rules are defined in a rule config block.

Because this resource only manages what it's told to, it will not manage any rules that may already exist on the firewall. This has implications on the effective security posture of your firewall, but it will allow you to spread your security rules across multiple Terraform state files. If you want to verify that the security rules are only what appears in the plan file, then you should probably be using the panos_security_policy resource.

Although you cannot modify non-group security rules with this resource, the position_keyword and position_reference parameters allow you to reference some other security rule that already exists, using it as a means to ensure some rough placement within the ruleset as a whole.

For each security rule, there are three styles of profile settings:

- None (the default)
- Group
- Profiles

The Profile Setting is implicitly chosen based on what params are configured for the security rule. If you want a Profile Setting of Group, then the group param should be set to the desired Group Profile. If you want a Profile Setting of Profiles, then you will need to specify one or more of the following params:

- virus
- spyware
- vulnerability
- url filtering
- file blocking
- wildfire_analysis
- data filtering

If the group param and none of the Profiles params are specified, then the Profile Setting is set to None.

» Best Practices

As is to be expected, if you are separating your deployment across multiple plan files, make sure that at most only one plan specifies any given absolute positioning keyword such as "top" or "directly below", otherwise they'll keep shoving each other out of the way indefinitely.

Best practices are to specify one group as top (if you need it), one group as bottom (this is where you have your logging deny rule), then all other groups should be above the first rule of the bottom group. You do it this way because rules will natually be added at the tail end of the rulebase, so they will always be after the first group, but what you want is for them to be before the last group's rules.

```
resource "panos_security_rule_group" "example" {
    position_keyword = "above"
    position reference = "deny everything else"
    rule {
        name = "allow bizdev to dmz"
        source_zones = ["bizdev"]
        source_addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["dmz"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "allow"
    }
    rule {
        name = "deny sales to eng"
        source_zones = ["sales"]
        source addresses = ["any"]
        source_users = ["any"]
        hip_profiles = ["any"]
        destination_zones = ["eng"]
        destination_addresses = ["any"]
        applications = ["any"]
        services = ["application-default"]
        categories = ["any"]
        action = "deny"
    }
}
```

The following arguments are supported:

- vsys (Optional) The vsys to put the security rule into (default: vsys1).
- position_keyword (Optional) A positioning keyword for this group. This can be before, directly before, after, directly after, top, bottom, or left empty (the default) to have no particular placement. This param works in combination with the position reference param.
- position_reference (Optional) Required if position_keyword is one of the "above" or "below" variants, this is the name of a non-group rule to use as a reference to place this group.
- rule The security rule definition (see below). The security rule ordering will match how they appear in the terraform plan file.

The following arguments are valid for each rule section:

- name (Required) The security rule name.
- type (Optional) Rule type. This can be universal (default), interzone, or intrazone.
- description (Optional) The description.
- tags (Optional) List of tags for this security rule.
- source_zones (Required) List of source zones.
- source_addresses (Required) List of source addresses.
- negate_source (Optional, bool) If the source should be negated.
- source_users (Required) List of source users.
- hip_profiles (Required) List of HIP profiles.
- destination zones (Required) List of destination zones.
- destination_addresses (Required) List of destination addresses.
- negate_destination (Optional, bool) If the destination should be negated.
- applications (Required) List of applications.
- services (Required) List of services.
- categories (Required) List of categories.
- action (Optional) Action for the matched traffic. This can be allow (default), deny, drop, reset-client, reset-server, or reset-both.
- log_setting (Optional) Log forwarding profile.
- log_start (Optional, bool) Log the start of the traffic flow.
- log_end (Optional, bool) Log the end of the traffic flow (default: true).
- disabled (Optional, bool) Set to true to disable this rule.
- schedule (Optional) The security rule schedule.
- icmp unreachable (Optional) Set to true to enable ICMP unreachable.
- disable_server_response_inspection (Optional) Set to true to disable server response inspection.
- group (Optional) Profile Setting: Group The group profile name.
- virus (Optional) Profile Setting: Profiles The antivirus setting.
- spyware (Optional) Profile Setting: Profiles The anti-spyware set-

ting.

- vulnerability (Optional) Profile Setting: Profiles The Vulnerability Protection setting.
- url_filtering (Optional) Profile Setting: Profiles The URL filtering setting.
- file_blocking (Optional) Profile Setting: Profiles The file blocking setting.
- wildfire_analysis (Optional) Profile Setting: Profiles The Wild-Fire Analysis setting.
- data_filtering (Optional) Profile Setting: Profiles The Data Filtering setting.

» panos_service_group

This resource allows you to add/update/delete service groups.

» Example Usage

```
resource "panos_service_group" "example" {
   name = "static ntp grp"
   services = ["svc1", "svc2"]
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The service group's name.
- vsys (Optional) The vsys to put the service group into (default: vsys1).
- services (Required) List of services to put in this service group.
- tags (Optional) List of administrative tags.

» panos_service_object

This resource allows you to add/update/delete service objects.

```
resource "panos_service_object" "example" {
   name = "my_service"
```

```
vsys = "vsys1"
protocol = "tcp"
description = "My service object"
source_port = "2000-2049,2051-2099"
destination_port = "32123"
tags = ["internal", "dmz"]
}
```

The following arguments are supported:

- name (Required) The service object's name.
- vsys (Optional) The vsys to put the service object into (default: vsys1).
- description (Optional) The service object's description.
- protocol (Required) The service's protocol. This should be tcp or udp.
- source_port (Optional) The source port. This can be a single port number, range (1-65535), or comma separated (80,8080,443).
- destination_port (Required) The destination port. This can be a single port number, range (1-65535), or comma separated (80,8080,443).
- tags (Optional) List of administrative tags.

» panos_telemetry

This resource allows you to add/update/delete telemetry sharing.

Join other Palo Alto Networks customers in a global sharing community, helping to raise the bar against the latest attack techniques. Your participation allows us to deliver new threat prevention controls across the attack lifecycle. Choose the type of data you share across applications, threat intelligence, and device health information to improve the fidelity of the protections we deliver. This is an opt-in feature controlled with granular policy, and we encourage you to join the community.

```
resource "panos_telemetry" "example" {
   threat_prevention_reports = true
   threat_prevention_data = true
   threat_prevention_packet_captures = true
}
```

The following arguments are supported:

- application_reports (Bool, optional) Application reports.
- threat_prevention_reports (Bool, optional) Threat reports.
- url_reports (Bool, optional) URL reports.
- file_type_identification_reports (Bool, optional) File type identification reports.
- threat_prevention_data (Bool, optional) Threat prevention data.
- threat_prevention_packet_captures (Bool, optional) Enable sending packet- captures with threat prevention information. This requires that threat_prevention_data also be enabled.
- product_usage_stats (Bool, optional) Health and performance reports.
- passive_dns_monitoring (Bool, optional) Passive DNS monitoring.

» panos virtual router

This resource allows you to add/update/delete virtual routers.

Note - The default virtual router may be configured with this resource, however it will not be deleted from the firewall. It will only be unexported from the vsys that it is currently imported in, and any interfaces imported into the virtual router will be removed.

» Example Usage

```
# Configure a bare-bones ethernet interface.
resource "panos_virtual_router" "example" {
    name = "my virtual router"
    static_dist = 15
    interfaces = ["ethernet1/1", "ethernet1/2"]
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The virtual router's name.
- vsys (Required) The vsys that will use this virtual router. This should be something like vsys1 or vsys3.
- interfaces (Optional) List of interfaces that should use this virtual router.
- static_dist (Optional) Admin distance Static (default: 10).

- static_ipv6_dist (Optional) Admin distance Static IPv6 (default: 10).
- ospf_int_dist (Optional) Admin distance OSPF Int (default: 30).
- ospf_ext_dist (Optional) Admin distance OSPF Ext (default: 110).
- ospfv3_int_dist (Optional) Admin distance OSPFv3 Int (default: 30).
- ospfv3_ext_dist (Optional) Admin distance OSPFv3 Ext (default: 110).
- ibgp_dist (Optional) Admin distance IBGP (default: 200).
- ebgp_dist (Optional) Admin distance EBGP (default: 20).
- rip_dist (Optional) Admin distance RIP (default: 120).

» panos_zone

This resource allows you to add/update/delete zones.

» Example Usage

```
resource "panos_zone" "example" {
   name = "my_service"
   mode = "layer3"
   interfaces = ["ethernet1/1", "ethernet1/2"]
   enable_user_id = true
   exclude_acls = ["192.168.0.0/16"]
}
```

» Argument Reference

The following arguments are supported:

- name (Required) The zone's name.
- vsys (Optional) The vsys to put the zone into (default: vsys1).
- mode (Required) The zone's mode. This can be layer3, layer2, virtual-wire, tap, or tunnel.
- zone_profile (Optional) The zone protection profile.
- log_setting (Optional) Log setting.
- enable_user_id (Optional) Boolean to enable user identification.
- interfaces (Optional) List of interfaces to associated with this zone.
- include_acls (Optional) Users from these addresses/subnets will be identified. This can be an address object, an address group, a single IP address, or an IP address subnet.

• exclude_acls - (Optional) Users from these addresses/subnets will not be identified. This can be an address object, an address group, a single IP address, or an IP address subnet.