» exoscale_compute

Provides information on an Compute instance hosted on Exoscale Compute.

» Example Usage

```
data "exoscale_compute" "my_server" {
  hostname = "my server"
}
```

» Argument Reference

- hostname The hostname of the Compute instance.
- id The ID of the Compute instance.
- tags The tags to find the Compute instance.

» Attributes Reference

The following attributes are exported:

- id ID of the Compute instance.
- hostname Hostname of the Compute instance.
- tags Map of tags (key: value).
- created Date when the Compute instance was created.
- zone Name of the zone.
- template Name of the template.
- size Current size of the Compute instance.
- disk_size Size of the Compute instance disk.
- cpu Number of cpu the Compute instance is running with.
- memory Memory allocated for the Compute instance.
- state State of the Compute instance.
- ip_address Public IPv4 address of the Compute instance.
- ip6_address Public IPv6 address of the Compute instance (if IPv6 is enabled).
- private_network_ip_addresses List of Compute private IP addresses (in managed Private Networks only).

» exoscale_compute_template

Provides information on an Compute IP Address.

» Example Usage

```
locals {
   zone = "ch-gva-2"
}

data "exoscale_compute_ipaddress" "eip" {
   zone = "${local.zone}"
   ip_address = "159.162.3.4"
}
```

» Argument Reference

- zone (Required) The name of the zone where to look for the IP Address.
- ip_address The IP Address of the EIP.
- id The ID of the IP Address.
- description The Description to find the IP Address.
- tags The tags to find the IP Address.

» Attributes Reference

The following attributes are exported:

- zone Name of the zone.
- ip_address IP Address.
- id ID of the IP Address.
- description Description of the IP.
- tags Map of tags (key: value).

» exoscale_compute_template

Provides information on an Compute template for use in other resources such as a exoscale_compute resource.

```
locals {
   zone = "ch-gva-2"
}
data "exoscale_compute_template" "ubuntu" {
   zone = local.zone
```

- zone (Required) The name of the zone where to look for the Compute template.
- name The name of the Compute template.
- id The ID of the Compute template.
- filter A Compute template search filter, must be either featured (official Exoscale templates), community (community-contributed templates) or mine (custom templates private to my organization). Default is featured.

» Attributes Reference

The following attributes are exported:

- id ID of the template
- name Name of the template
- username Username to use to log into a Compute Instance based on this template

» exoscale_domain

Provides information on a domain name hosted on Exoscale DNS.

```
data "exoscale_domain" "my-company-com" {
  name = "my-company.com"
}
```

• name - (Required) The name of the domain.

» Attributes Reference

The following attributes are exported:

- name Name of the Domain
- id ID of the Domain

» exoscale_domain_record

Provides information on domain records hosted on Exoscale DNS.

» Example Usage

The example below matches all Domain Records that match with name mailserver and Record type MX.

```
data "exoscale_domain" "mycompany" {
   name = my-company.com
}

data "exoscale_domain_record" "mycompany_mailservers" {
   domain = data.exoscale_domain.mycompany.name
   filter {
     name = "mailserver"
     recorde_type = "MX"
   }
}

data "exoscale_domain_record" "mycompany_nameservers" {
   domain = data.exoscale_domain.mycompany.name
   filter {
     content_regex = "ns.*"
   }
}

output "first_domain_record_name" {
   value = $(data.exoscale_domain_record.mycompany_mailservers.records.0.name)
}
```

```
output "first_domain_record_content" {
  value = $(data.exoscale_domain_record.mycompany_nameservers.records.0.content)
}
```

- domain (Required) The name of the domain where to look for Domain Records
- filter- (Required) One value is used to look up Domain Records or name and record_type together.

filter

- name The name matching the Domain Record name to lookup.
- id The ID matching the Domain Record ID to lookup.
- record_type The Record type matching the Domain Record type to lookup.
- content_regex A regular expression matching the Domain Record content to lookup.

» Attributes Reference

The following attributes are exported:

records

- id Domain Record ID
- domain Domain Name where the Record is associate to.
- name Domain Record name
- content Domain Record content
- record_type Domain Record type
- prio Domain Record prio

» exoscale_affinity

Provides an Exoscale Anti-Affinity Group. This can be used to create and delete Anti-Affinity Groups.

```
type = "host anti-affinity"
}
```

- name (Required) The name of the Anti-Affinity Group.
- description A free-form text describing the Anti-Affinity Group purpose.
- type The type of the Anti-Affinity Group (host anti-affinity is the only supported value).

» Attributes Reference

The following attributes are exported:

- id The ID of the Anti-Affinity Group.
- virtual_machine_ids The IDs of the Compute instance resources member of the Anti-Affinity Group.

» Import

An existing Anti-Affinity Group can be imported as a resource by name or ID:

```
# By name
$ terraform import exoscale_affinity.mygroup mygroup

# By ID
$ terraform import exoscale_affinity.mygroup eb556678-ec59-4be6-8c54-0406ae0f6da6
```

» exoscale compute

Provides an Exoscale Compute instance resource. This can be used to create, modify, and delete Compute instances.

```
data "exoscale_compute_template" "ubuntu" {
  zone = "ch-gva-2"
  name = "Linux Ubuntu 18.04 LTS 64-bit"
}
resource "exoscale_compute" "mymachine" {
```

```
= "ch-gva-2"
  zone
 display_name = "mymachine"
  template_id = data.exoscale_compute_template.ubuntu.id
               = "Medium"
  size
 disk_size
               = 10
               = "me@mymachine"
 key_pair
               = "Running"
  state
  affinity_groups = []
  security_groups = ["default"]
  ip6 = false
 user data = <<EOF
#cloud-config
manage etc hosts: localhost
EOF
  tags = {
    production = "true"
  timeouts {
    create = "60m"
    delete = "2h"
}
```

- zone (Required) The name of the zone to deploy the Compute instance into.
- template (Required) The name of the Compute instance template. Only featured templates are available, if you want to reference custom templates use the template_id attribute instead.
- template_id (Required) The ID of the Compute instance template. Usage of the compute_template data source is recommended.
- size (Required) The Compute instance size, e.g. Tiny, Small, Medium, Large etc.
- disk_size (Required) The Compute instance root disk size in GiB (at least 10).
- display_name The displayed name of the Compute instance. Note: if the hostname attribute is not set, this attribute is also used to set the OS' hostname during creation, so the value must contain only alphanumeric and hyphen ("-") characters; it can be changed to any character during a

- later update. If neither display_name or hostname attributes are set, a random value will be generated automatically server-side.
- hostname The Compute instance hostname, must contain only alphanumeric and hyphen ("-") characters. If neither display_name or hostname attributes are set, a random value will be generated automatically serverside. Note: updating this attribute's value requires to reboot the instance.
- key_pair The name of the SSH key pair to be installed.
- user_data A cloud-init configuration. Whenever possible don't base64encode neither gzip it yourself, as this will be automatically taken care of on your behalf by the provider.
- keyboard The keyboard layout configuration (at creation time only). Supported values are: de, de-ch, es, fi, fr, fr-be, fr-ch, is, it, jp, nl-be, no, pt, uk, us.
- state The state of the Compute instance, e.g. Running or Stopped
- affinity_groups A list of Anti-Affinity Group names (at creation time only; conflicts with affinity_group_ids).
- affinity_group_ids A list of Anti-Affinity Group IDs (at creation time only; conflicts with affinity_groups).
- security_groups A list of Security Group names (conflicts with security_group_ids).
- security_group_ids A list of Security Group IDs (conflicts with security_groups).
- ip4 Boolean controlling if IPv4 is enabled (only supported value is true).
- ip6 Boolean controlling if IPv6 is enabled.
- tags A dictionary of tags (key/value).

» Attributes Reference

The following attributes are exported:

- name Deprecated The Compute instance *hostname*. Use the hostname attribute instead.
- username The user to use to connect to the Compute instance with SSH. If you've referenced a *custom template* in the resource, use the compute_template data source username attribute instead.
- password The initial Compute instance password and/or encrypted password.
- ip_address The IP address of the Compute instance main network interface.
- ip6_address The IPv6 address of the Compute instance main network interface.

» remote-exec provisioner usage

If you wish to log to a exoscale_compute resource using the remote-exec provisioner, make sure to explicity set the SSH user setting to connect to the instance to the actual template username returned by the exoscale_compute_template data source:

```
data "exoscale_compute_template" "ubuntu" {
  zone = "ch-gva-2"
 name = "Linux Ubuntu 18.04 LTS 64-bit"
}
resource "exoscale_compute" "mymachine" {
              = "ch-gva-2"
  zone
 display_name = "mymachine"
  template_id = data.exoscale_compute_template.ubuntu.id
              = "Medium"
  size
  disk_size = 10
 key_pair = "me@mymachine"
state = "Running"
 provisioner "remote-exec" {
    connection {
      type = "ssh"
     host = self.ip_address
      user = data.exoscale_compute_template.ubuntu.username
    }
 }
}
```

» Import

An existing Compute instance can be imported as a resource by name or ID. Importing a Compute instance imports the exoscale_compute resource as well as related exoscale_secondary_ipaddress and exoscale_nic resources.

```
# By name
$ terraform import exoscale_compute.vm1 vm1

# By ID
$ terraform import exoscale_compute.vm1 eb556678-ec59-4be6-8c54-0406ae0f6da6
```

» exoscale_domain

Provides an Exoscale DNS Domain resource. This can be used to create and delete DNS Domains.

» Usage example

```
resource "exoscale_domain" "example" {
  name = "example.net"
}
```

» Argument Reference

• name - (Required) The name of the DNS Domain.

» Attributes Reference

The following attributes are exported:

- token A security token that can be used as an alternative way to manage DNS Domains via the Exoscale API.
- state The state of the DNS Domain.
- auto_renew Boolean indicating that the DNS Domain has automatic renewal enabled.
- expires_on The date of expiration of the DNS Domain, if known.

» Import

An existing DNS Domain can be imported as a resource by name:

```
$ terraform import exoscale_domain.example example.net
```

NOTE: importing a exoscale_domain resource will also import all related [exoscale_domain_records][domainrec] resources (except NS and SOA).

» exoscale_domain_record

Provides an Exoscale DNS Domain Record resource. This can be used to create, modify, and delete DNS Domain Records.

» Usage example

```
resource "exoscale domain" "example" {
  name = "example.net"
resource "exoscale_domain_record" "myserver" {
              = exoscale domain.example.id
 domain
 name
              = "myserver"
 record_type = "A"
  content
             = "1.2.3.4"
}
resource "exoscale_domain_record" "myserver_alias" {
             = exoscale_domain.example.id
  domain
 name
              = "myserver-new"
 record_type = "CNAME"
             = exoscale_domain_record.myserver.hostname
  content
}
```

» Argument Reference

- domain (Required) The name of the exoscale_domain to create the record into.
- name (Required) The name of the DNS Domain Record.
- record_type (Required) The type of the DNS Domain Record. Supported values are: A, AAAA, ALIAS, CAA, CNAME, HINFO, MX, NAPTR, NS, POOL, SPF, SRV, SSHFP, TXT, URL.
- content (Required) The value of the DNS Domain Record.
- ttl The Time To Live of the DNS Domain Record.
- prio The priority of the DNS Domain Record (for types that support it).

» Attributes Reference

The following attributes are exported:

• hostname - The DNS Domain Record's Fully Qualified Domain Name (FQDN), useful for linking A records into CNAME.

» Import

An existing DNS Domain Record can be imported as a resource by ID:

\$ terraform import exoscale_domain_record.www 12480484

NOTE: importing an existing exoscale_domain resource also imports linked exoscale_domain_record resources.

» exoscale_instance_pool

Provides an Exoscale Instance Pool resource. This can be used to create, modify, and delete Instance Pools.

```
resource "exoscale_ssh_keypair" "key" {
 name = "terraform-mywebapp-keypair"
variable "zone" {
  default = "de-fra-1"
resource "exoscale_security_group" "web" {
 name = "web"
 description = "Security Group for webapp production"
}
resource "exoscale_network" "web_privnet" {
 zone = var.zone
 name = "web-privnet"
}
data "exoscale_compute_template" "mywebapp" {
 zone = var.zone
 name = "mywebapp"
 filter = "mine"
resource "exoscale_instance_pool" "webapp" {
 zone = var.zone
 name = "webapp"
 template_id = data.exoscale_compute_template.mywebbapp.id
  size = 3
 service_offering = "Medium"
 disk_size = 50
 description = "This is the production environment for my webapp"
```

```
user_data = "#cloud-config\npackage_upgrade: true\n"
key_pair = exoscale_ssh_keypair.key.name

security_group_ids = [${exoscale_security_group.web.id}]
network_ids = [${exoscale_network.web_privnet.id}]

timeouts {
    delete = "10m"
}
```

- zone (Required) The name of the zone to deploy the Instance Pool into.
- name (Required) The name of the Instance Pool.
- template_id (Required) (Required) The ID of the instance template to use when creating Compute instances. Usage of the compute_template data source is recommended.
- size (Required) The number of Compute instance members the Instance Pool manages.
- service_offering (Required) The managed Compute instances size, e.g. Tiny, Small, Medium, Large etc.
- disk_size The managed Compute instances disk size.
- description The description of the Instance Pool.
- user_data A cloud-init configuration to apply when creating Compute
 instances. Whenever possible don't base64-encode neither gzip it yourself,
 as this will be automatically taken care of on your behalf by the provider.
- key_pair The name of the SSH key pair to install when creating Compute instances.
- security_group_ids A list of [Security Group][sg] IDs.
- network_ids A list of Private Network IDs.

» Import

An existing Instance Pool can be imported as a resource by name or ID. Importing an Instance Pool imports the exoscale_instance_pool resource.

```
# By name
$ terraform import exoscale_instance_pool.pool mypool

# By ID
$ terraform import exoscale_instance_pool.pool eb556678-ec59-4be6-8c54-0406ae0f6da6
```

» exoscale_ipaddress

Provides an Exoscale Elastic IP resource. This can be used to create, update and delete Elastic IPs.

See exoscale_secondary_ipaddress for usage with Compute instances.

» Usage example

```
resource "exoscale_ipaddress" "myip" {
  zone = "ch-dk-2"
  tags = {
   usage = "load-balancer"
}
Managed EIP:
resource "exoscale_ipaddress" "myip" {
  zone
                           = "ch-dk-2"
 description
                           = "My elastic IP for load balancer"
 healthcheck mode
                           = "http"
 healthcheck_port
                           = 8000
 healthcheck_path
                           = "/status"
 healthcheck_interval
                           = 5
 healthcheck_timeout
 healthcheck_strikes_ok
                           = 2
  healthcheck_strikes_fail = 3
}
```

» Argument Reference

- zone (Required) The name of the zone to create the Elastic IP into.
- description The description of the Elastic IP.
- healthcheck_mode The healthcheck probing mode (must be either tcp or http).
- healthcheck_port The healthcheck service port to probe (must be between 1 and 65535).
- healthcheck_path The healthcheck probe HTTP request path (must be specified in http mode).
- healthcheck_interval The healthcheck probing interval in seconds (must be between 5 and 300).
- healthcheck_timeout The time in seconds before considering a healthcheck probing failed (must be between 2 and 60).

- healthcheck_strikes_ok The number of successful healthcheck probes before considering the target healthy (must be between 1 and 20).
- healthcheck_strikes_fail The number of unsuccessful healthcheck probes before considering the target unhealthy (must be between 1 and 20)
- tags A dictionary of tags (key/value).

» Attributes Reference

The following attributes are exported:

• ip_address - The Elastic IP address.

» Import

An existing Elastic IP can be imported as a resource by address or ID:

```
# By address
$ terraform import exoscale_ipaddress.myip 159.100.251.224
# By ID
$ terraform import exoscale_ipaddress.myip eb556678-ec59-4be6-8c54-0406ae0f6da6
```

» exoscale_network

Provides an Exoscale Private Network resource. This can be used to create, update and delete Private Networks.

See exoscale_nic for usage with Compute instances.

» Usage

Managed Private Network (~> **NOTE:** this feature is currently only available in the ch-gva-2 zone):

» Argument Reference

- zone (Required) The name of the zone to create the Private Network into.
- name (Required) The name of the Private Network.
- display_text A free-form text describing the Private Network purpose.
- start_ip The first address of IP range used by the DHCP service to automatically assign. Required for *managed* Private Networks.
- end_ip The last address of the IP range used by the DHCP service.
 Required for managed Private Networks.
- netmask The netmask defining the IP network allowed for the static lease (see exoscale_nic resource). Required for managed Private Networks.
- tags A dictionary of tags (key/value).

» Import

An existing Private Network can be imported as a resource by name or ID:

```
# By name
$ terraform import exoscale_network.net myprivnet

# By ID
$ terraform import exoscale_network.net 04fb76a2-6d22-49be-8da7-f2a5a0b902e1
```

» exoscale_nic

Provides an Exoscale Compute instance Private Network Interface (NIC) resource. This can be used to create, update and delete Compute instance NICs.

» Usage

```
resource "exoscale_compute" "vm1" {
    ...
}

resource "exoscale_network" "oob" {
    ...
}

resource "exoscale_nic" "oob" {
    compute_id = exoscale_compute.vm1.id
    network_id = exoscale_network.oob.id
}
```

» Argument Reference

- compute_id (Required) The Compute instance ID.
- network_id (Required) The Private Network ID.
- ip_address The IP address to request as static DHCP lease if the NIC is attached to a *managed* Private Network (see the exoscale_network resource).

» Attributes Reference

The following attributes are exported:

• mac_address - The physical address (MAC) of the Compute instance NIC.

» Import

This resource is automatically imported when importing an exoscale_compute resource.

» exoscale_security_group

Provides an Exoscale Security Group resource. This can be used to create and delete Security Groups.

» Example usage

» Argument Reference

The following attributes are exported:

- name (Required) The name of the Security Group.
- description A free-form text describing the Anti-Affinity Group purpose.
- tags A dictionary of tags (key/value).

» Import

An existing Security Group can be imported as a resource by name or ID:

```
# By name
$ terraform import exoscale_security_group.http http

# By ID
$ terraform import exoscale_security_group.http eb556678-ec59-4be6-8c54-0406ae0f6da6

NOTE: Importing a exoscale_security_group resource also imports related
exoscale_security_group_rule resources.
```

» exoscale_security_group_rule

Provides an Exoscale Security Group Rule resource. This can be used to create and delete Security Group Rules.

```
resource "exoscale_security_group" "webservers" {
    ...
}
```

```
resource "exoscale_security_group_rule" "http" {
  security_group_id = exoscale_security_group.webservers.id
  type = "INGRESS"
  protocol = "TCP"
  cidr = "0.0.0.0/0" # "::/0" for IPv6
  start_port = 80
  end_port = 80
}
```

- security_group (Required) The Security Group name the rule applies to.
- security_group_id (Required) The Security Group ID the rule applies to.
- type (Required) The traffic direction to match (INGRESS or EGRESS).
- protocol (Required) The network protocol to match. Supported values are: TCP, UDP, ICMP, ICMPv6, AH, ESP, GRE, IPIP and ALL.
- description A free-form text describing the Security Group Rule purpose.
- start_port/end_port A TCP/UDP port range to match.
- icmp_type/icmp_code An ICMP/ICMPv6 type/code to match.
- cidr A source (for ingress)/destination (for egress) IP subnet to match (conflicts with user_security_group).
- user_security_group_id A source (for ingress)/destination (for egress) Security Group ID to match (conflicts with cidr).
- user_security_group A source (for ingress)/destination (for egress) Security Group name to match (conflicts with cidr).

» Attributes Reference

The following attributes are exported:

- security_group The name of the Security Group the rule applies to.
- security_group_id The ID of the Security Group the rule applies to.
- user_security_group The name of the source (for ingress)/destination (for egress) Security Group to match.

» Import

This resource is automatically imported when importing an exoscale_security_group resource.

» exoscale_security_group_rules

Provides a resource for assigning multiple rules to an existing Exoscale Security Group.

» Example usage

```
resource "exoscale_security_group" "webservers" {
resource "exoscale_security_group_rules" "admin" {
  security_group = exoscale_security_group.webservers.name
  ingress {
                             = "ICMP"
   protocol
    icmp_type
    user_security_group_list = ["bastion"]
  }
  ingress {
                             = "TCP"
    protocol
                             = ["22"]
    ports
    user_security_group_list = ["bastion"]
}
resource "exoscale_security_group_rules" "web" {
  security_group_id = exoscale_security_group.webservers.id
  ingress {
    protocol = "TCP"
            = ["80", "443"]
    cidr list = ["0.0.0.0/0", "::/0"]
  }
}
```

» Argument Reference

The following attributes are exported:

• security_group - (Required) The Security Group name the rules apply to.

• security_group_id - (Required) The Security Group ID the rules apply to.

egress and ingress support the following:

- protocol (Required) The network protocol to match. Supported values are: TCP, UDP, ICMP, ICMPv6, AH, ESP, GRE, IPIP and ALL.
- description A free-form text describing the Security Group Rule purpose.
- ports A list of ports or port ranges (start_port-end_port).
- icmp_type/icmp_code An ICMP/ICMPv6 type/code to match.
- cidr_list A list of source (for ingress)/destination (for egress) IP subnet to match (conflicts with user_security_group).
- user_security_group_list A source (for ingress)/destination (for egress) of the traffic identified by a security group

» Attributes Reference

The following attributes are exported:

- security_group The name of the Security Group the rules apply to.
- security_group_id The ID of the Security Group the rules apply to.

» exoscale_secondary_ipaddress

Provides a resource for assigning an existing Exoscale Elastic IP to a Compute instance.

NOTE: The network interfaces of the Compute instance itself still have to be configured accordingly (unless using a *managed* Elastic IP).

» Secondary IP Address

```
resource "exoscale_compute" "vm1" {
    ...
}

resource "exoscale_ipaddress" "vip" {
    ...
}

resource "exoscale_secondary_ipaddress" "vip" {
    compute_id = exoscale_compute.vm1.id
    ip_address = exoscale_ipaddress.vip.ip_address
}
```

- compute_id (Required) The ID of the Compute instance.
- ip_address (Required) The Elastic IP address to assign.

» Attributes Reference

The following attributes are exported:

- nic_id The ID of the NIC.
- network_id The ID of the Network the Compute instance NIC is attached to.

» Import

This resource is automatically imported when importing an exoscale_compute resource.

» exoscale_ssh_keypair

Provides an Exoscale SSH Keypair resource. This can be used to create and delete SSH Keypairs.

» Example Usage

» Argument Reference

- name (Required) The name of the SSH Keypair.
- public_key A SSH public key that will be copied into the instances at first boot. If not provided, a SSH keypair is generated and the is saved locally (see the private_key attribute).

» Attributes Reference

The following attributes are exported:

- fingerprint The unique identifier of the SSH Keypair.
- public_key The SSH public key generated if none was provided.
- private_key The SSH private key generated if no public key was provided.

» Import

An existing SSH Keypair can be imported as a resource by name:

\$ terraform import exoscale_ssh_keypair.mykey my-key