# » nutanix\_virtual\_machine

Describes a Virtual Machine

# » Example Usage

```
data "nutanix_clusters" "clusters" {
metadata = {
 length = 2
}
}
output "cluster" {
value = data.nutanix_clusters.clusters.entities.0.metadata.uuid
resource "nutanix virtual machine" "vm1" {
name = "test-dou-%d"
cluster_uuid= data.nutanix_clusters.clusters.entities.0.metadata.uuid
num_vcpus_per_socket = 1
num_sockets
               = 1
memory_size_mib = 2048
                = "ON"
power_state
data "nutanix_virtual_machine" "nutanix_virtual_machine" {
vm_id = nutanix_virtual_machine.vm1.id
```

# » Argument Reference

The following arguments are supported:

• vm\_id: Represents virtual machine UUID

# » Attribute Reference

The following attributes are exported:

- name: The name for the vm.
- $\bullet\,$  cluster\_reference: - The reference to a cluster.
- cluster\_name: The name of the reference to the cluster.
- categories: Categories for the vm.

- project\_reference: The reference to a project.
- owner\_reference: The reference to a user.
- availability zone reference: The reference to a availability zone.
- api\_version The version of the API.
- description: A description for vm.
- num\_vnuma\_nodes: Number of vNUMA nodes. 0 means vNUMA is disabled.
- nic\_list: NICs attached to the VM.
- serial\_port\_list: (Optional) Serial Ports configured on the VM.
- guest\_os\_id: Guest OS Identifier. For ESX, refer to VMware documentation link for the list of guest OS identifiers.
- power\_state: The current or desired power state of the VM. (Options: ON, OFF)
- nutanix guest tools: Information regarding Nutanix Guest Tools.
- ngt\_credentials: Credentials to login server.
- ngt\_enabled\_capability\_list Application names that are enabled.
- num\_vcpus\_per\_socket: Number of vCPUs per socket.
- num\_sockets: Number of vCPU sockets.
- gpu\_list: GPUs attached to the VM.
- parent\_referece: Reference to an entity that the VM cloned from.
- memory\_size\_mib: Memory size in MiB.
- boot\_device\_order\_list: Indicates the order of device types in which VM should try to boot from. If boot device order is not provided the system will decide appropriate boot device order.
- boot\_device\_disk\_address: Address of disk to boot from.
- boot device mac address: MAC address of nic to boot from.
- hardware\_clock\_timezone: VM's hardware clock timezone in IANA TZDB format (America/Los\_Angeles).
- guest\_customization\_cloud\_init\_user\_data: The contents of the user\_data configuration for cloud-init. This can be formatted as YAML, JSON, or could be a shell script. The value must be base64 encoded.
- guest\_customization\_cloud\_init\_meta\_data The contents of the meta\_data configuration for cloud-init. This can be formatted as YAML or JSON. The value must be base64 encoded.
- guest\_customization\_is\_overridable: Flag to allow override of customization by deployer.
- guest\_customization\_cloud\_init\_custom\_key\_values: Generic key value pair used for custom attributes in cloud init.
- guest\_customization\_sysprep: VM guests may be customized at boot time using one of several different methods. Currently, cloud-init w/ ConfigDriveV2 (for Linux VMs) and Sysprep (for Windows VMs) are supported. Only ONE OF sysprep or cloud\_init should be provided. Note that guest customization can currently only be set during VM creation. Attempting to change it after creation will result in an error. Additional properties can be specified. For example in the context of VM template creation if \"override\_script\" is set to \"True\" then the deployer can

- upload their own custom script.
- guest\_customization\_sysrep\_custom\_key\_values: Generic key value pair used for custom attributes in sysrep.
- should\_fail\_on\_script\_failure: Extra configs related to power state transition. Indicates whether to abort ngt shutdown/reboot if script fails.
- enable\_script\_exec: Extra configs related to power state transition. Indicates whether to execute set script before ngt shutdown/reboot.
- power\_state\_mechanism: Indicates the mechanism guiding the VM power state transition. Currently used for the transition to \"OFF\" state. Power state mechanism (ACPI/GUEST/HARD).
- vga\_console\_enabled: Indicates whether VGA console should be enabled or not.
- disk\_list Disks attached to the VM.
- metadata: The vm kind metadata.
- state: The state of the vm.
- ip address: An IP address.
- host\_reference: Reference to a host.
- hypervisor\_type: The hypervisor type for the hypervisor the VM is hosted on.

### » Disk List

The disk list attribute supports the following:

- UUID: The device ID which is used to uniquely identify this particular disk.
- disk\_size\_bytes Size of the disk in Bytes.
- disk\_size\_mib Size of the disk in MiB. Must match the size specified in 'disk\_size\_bytes' rounded up to the nearest MiB when that field is present.
- device\_properties Properties to a device.
- data\_source\_reference Reference to a data source.
- volume\_group\_reference Reference to a volume group.

### » Device Properties

The device\_properties attribute supports the following.

- device\_type: A Disk type (default: DISK).
- disk\_address: Address of disk to boot from.

# » Sysprep

The guest\_customization\_sysprep attribute supports the following:

- install\_type: Whether the guest will be freshly installed using this unattend configuration, or whether this unattend configuration will be applied to a pre-prepared image. Default is \"PREPARED\".
- unattend\_xml: Generic key value pair used for custom attributes.

### » Disk Address

The boot\_device\_disk\_address attribute supports the following:

- device\_index: The index of the disk address.
- adapter\_type: The adapter type of the disk address.

### » GPU List

The gpu list attribute supports the following:

- frame\_buffer\_size\_mib: GPU frame buffer size in MiB.
- vendor: The vendor of the GPU.
- UUID: UUID of the GPU.
- name: Name of the GPU resource.
- pci\_address GPU {segment:bus:device:function} (sbdf) address if assigned.
- fraction Fraction of the physical GPU assigned.
- mode: The mode of this GPU.
- num\_virtual\_display\_heads: Number of supported virtual display heads.
- guest\_driver\_version: Last determined guest driver version.
- device\_id: (Computed) The device ID of the GPU.

### » Nutanix Guest Tools

The nutanix\_guest\_tools attribute supports the following:

- state: Nutanix Guest Tools is enabled or not.
- ngt\_state: Nutanix Guest Tools is enabled or not.
- iso\_mount\_state: Desired mount state of Nutanix Guest Tools ISO.
- version: Version of Nutanix Guest Tools installed on the VM.
- available\_version: Version of Nutanix Guest Tools available on the cluster.
- guest\_os\_version: Version of the operating system on the VM.
- vss\_snapshot\_capable: Whether the VM is configured to take VSS snapshots through NGT.
- is reachable: Communication from VM to CVM is active or not.
- vm\_mobility\_drivers\_installed: Whether VM mobility drivers are installed in the VM.

### » NIC List

The nic\_list attribute supports the following:

- nic\_type: The type of this NIC. Defaults to NORMAL\_NIC. (Options : NORMAL\_NIC , DIRECT\_NIC , NETWORK\_FUNCTION\_NIC).
- uuid: The NIC's UUID, which is used to uniquely identify this particular NIC. This UUID may be used to refer to the NIC outside the context of the particular VM it is attached to.
- floating\_ip: The Floating IP associated with the vnic.
- model: The model of this NIC. (Options: VIRTIO, E1000).
- network\_function\_nic\_type: The type of this Network function NIC. Defaults to INGRESS. (Options: INGRESS, EGRESS, TAP).
- mac\_address: The MAC address for the adapter.
- ip\_endpoint\_list: IP endpoints for the adapter. Currently, IPv4 addresses are supported.
- network\_function\_chain\_reference: The reference to a network function chain.
- subnet\_uuid: The reference to a subnet.
- subnet\_name: The name of the subnet reference to.

### » Serial Port List

The serial\_port\_list attribute supports the following:

- index: Index of the serial port (int).
- is\_connected: Indicates whether the serial port connection is connected or not (true or false).

### » ip\_endpoint\_list

The following attributes are exported:

- ip: Address string.
- type: Address type. It can only be "ASSIGNED" in the spec. If no type is specified in the spec, the default type is set to "ASSIGNED". (Options : ASSIGNED , LEARNED)

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when vm was last updated.
- UUID: vm UUID.

- creation\_time: UTC date and time in RFC-3339 format when vm was created
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: vm name.

### » Categories

The categories attribute supports the following:

- name: the key name.
- value: value of the key.

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, network\_function\_chain\_reference, data\_source\_reference, volume\_group\_reference attributes supports the following:

- kind: The kind name (Default value: project).
- name: the name.
- uud: the UUID.

See detailed information in Nutanix Virtual Machine.

# » nutanix\_volume\_group

Describes a Volume Group

# » Example Usage

The following arguments are supported:

• volume group id: Represents volume group UUID

### » Attribute Reference

The following attributes are exported:

- name: (Required) The name for the volume\_group.
- categories: (Optional) Categories for the volume\_group.
- project\_reference: (Optional) The reference to a project.
- owner\_reference: (Optional) The reference to a user.
- api\_version (Optional) Version of the API.
- description: (Optional) A description for volume group.
- flash\_mode: (Optional) Flash Mode, if enabled all volume disks of the VG will be pinned to SSD tier.
- file\_system\_type: (Optional) File system to be used for volume.
- sharing\_status: (Optiional) Whether the volume group can be shared across multiple iSCSI initiators.
- attachment\_list: (Optional) VMs attached to volume group.
- disk\_list: (Optional) Volume group disk specification.
- iscsi\_target\_prefix: (Optional) iSCSI target prefix-name.
- metadata: The volume\_group kind metadata.
- state: The state of the Volume Group.

### » Disk List

The disk list attribute supports the following:

- vmdisk\_UUID: (Optional) The UUID of this volume disk.
- index: (Optional) Index of the volume disk in the group.
- data\_source\_reference: (Optional) Reference to a kind
- disk\_size\_mib: (Optional) Size of the disk in MiB.
- storage\_container\_UUID: (Optional) Container UUID on which to create the disk.

### » Attachment List

The attachment list attribute supports the following:

- vm\_reference: (Optional) Reference to a kind.
- iscsi\_initiator\_name: (Optional) Name of the iSCSI initiator of the workload outside Nutanix cluster.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when volume\_group was last updated.
- UUID: volume\_group UUID.
- creation\_time: UTC date and time in RFC-3339 format when volume\_group was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: volume\_group name.

#### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, cluster\_reference, attributes supports the following:

- kind: The kind name (Default value: project)(Required).
- name: the name(Optional).
- UUID: the UUID(Required).

Note:  $vm_reference$  and  $data_source_reference$  don't support name argument

See detailed information in Nutanix Volume Group.

# » nutanix\_image

Describes a Image

# » Example Usage

```
data "nutanix_image" "testname" {
   image_name = nutanix_image.test.name
}
```

The following arguments are supported:

- image\_id: Represents image UUID
- image\_name: Represents image name

### » Attribute Reference

The following attributes are exported:

- name: The name for the image.
- categories: Categories for the image.
- project\_reference: The reference to a project.
- owner\_reference: The reference to a user.
- availability\_zone\_reference: The reference to a availability\_zone.
- api\_version -
- description: A description for image.
- architecture: The supported CPU architecture for a disk image.
- checksum: Checksum of the image. The checksum is used for image validation if the image has a source specified. For images that do not have their source specified the checksum is generated by the image service.
- image\_type: The type of image.
- source\_uri: The source URI points at the location of the source image which is used to create/update image.
- version: The image version.
- metadata: The image kind metadata.
- retrieval\_uri\_list: List of URIs where the raw image data can be accessed.
- size\_bytes: The size of the image in bytes.
- state: The state of the image.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when image was last updated.
- UUID: image UUID.
- creation\_time: UTC date and time in RFC-3339 format when image was created.

- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: image name.

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, cluster\_reference, attributes supports the following:

- kind: The kind name (Default value: project).
- name: the name.
- uuid: the UUID.

### » Version

The version attribute supports the following:

- product\_name: Name of the producer/distribution of the image. For example windows or red hat.
- product\_version: Version string for the disk image.

See detailed information in Nutanix Image.

# » nutanix subnet

Provides a resource to create a subnet based on the input parameters. A subnet is a block of IP addresses.

# » Example Usage

```
data "nutanix_clusters" "clusters" {
  metadata = {
    length = 2
  }
}

output "cluster" {
  value = data.nutanix_clusters.clusters.entities.0.metadata.uuid
}

resource "nutanix_subnet" "test" {
  name = "example-subnet"
```

```
cluster_reference = {
 kind = "cluster"
 UUID = data.nutanix_clusters.clusters.entities.0.metadata.uuid
}
 vlan_id = 201
  subnet_type = "VLAN"
 prefix_length = 24
 default_gateway_ip = "192.168.0.1"
  subnet_ip = "192.168.0.0"
  #ip_config_pool_list_ranges = ["192.168.0.5", "192.168.0.100"]
  dhcp options {
   boot_file_name = "bootfile"
   tftp_server_name = "192.168.0.252"
   domain_name = "nutanix"
 }
 dhcp_domain_name_server_list = ["8.8.8.8", "4.2.2.2"]
  dhcp_domain_search_list = ["nutanix.com", "calm.io"]
}
data "nutanix_subnet" "test" {
  subnet_id = nutanix_subnet.test.id
data "nutanix_subnet" "test-name" {
  subnet_name = nutanix_subnet.test.name
```

The following arguments are supported:

- subnet\_id: (Optional) The ID for the subnet.
- subnet\_name: (Optional) The name for the subnet

# » Attributes Reference

The following attributes are exported:

- metadata: (Required) The subnet kind metadata.
- availability\_zone\_reference: (Optional) The reference to a availability\_zone.

- cluster\_reference: (Optional) The reference to a cluster.
- cluster\_name: (Optional) The name of a cluster.
- description: (Optional) A description for subnet.
- name: (Optional) Subnet name (Readonly).
- categories: (Optional) The API Version.
- owner\_reference: (Optional) The reference to a user.
- project\_reference: (Optional) The reference to a project.
- vswitch\_name: (Optional).
- subnet\_type: (Optional).
- default\_gateway\_ip: (Optional) Default gateway IP address.
- prefix\_length: (Optional). IP prefix length of the Subnet.
- subnet\_ip: (Optional) Subnet IP address.
- dhcp\_server\_address: (Optional) Host address.
- dhcp server address port: (Optional) Port Number.
- dhcp\_options: (Optional) Spec for defining DHCP options.
- dhcp\_domain\_search\_list: (Optional).
- vlan\_id: (Optional).
- network\_function\_chain\_reference: (Optional) The reference to a network function chain.
- state: The state of the subnet.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when subnet was last updated.
- UUID: subnet UUID.
- creation\_time: UTC date and time in RFC-3339 format when subnet was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: subnet name.

### » Categories

The categories attribute supports the following:

- name: the key name.
- value: value of the key.

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, cluster\_reference, network\_function\_chain\_reference, subnet\_reference.

attributes supports the following:

- kind: The kind name (Default value: project)(Required).
- name: the name(Optional).
- uuid: the UUID(Required).

Note: cluster\_reference, subnet\_reference does not support the attribute name

See detailed information in Nutanix Subnet.

# » nutanix network security rule

Describes a Network security rule

# » Example Usage (Isolate Development VMs from Production VMs and get its information)

```
resource "nutanix_network_security_rule" "isolation" {
               = "example-isolation-rule"
    description = "Isolation Rule Example"
   isolation_rule_action = "APPLY"
    isolation_rule_first_entity_filter_kind_list = ["vm"]
    isolation_rule_first_entity_filter_type
                                                 = "CATEGORIES_MATCH_ALL"
    isolation_rule_first_entity_filter_params {
       name = "Environment"
        values = ["Dev"]
    }
    isolation_rule_second_entity_filter_kind_list = ["vm"]
                                                  = "CATEGORIES_MATCH_ALL"
    isolation_rule_second_entity_filter_type
    isolation_rule_second_entity_filter_params {
       name = "Environment"
        values = ["Production"]
}
data "nutanix_network_security_rule" "test" {
 network_security_rule_id = "${nutanix_network_security_rule.isolation.id}"
}
```

The following arguments are supported:

• network security rule id: Represents network security rule UUID

### » Attribute Reference

The following attributes are exported:

The following arguments are supported:

- name: (Required) The name for the image.
- categories: (Optional) Categories for the image.
- project\_reference: (Optional) The reference to a project.
- owner\_reference: (Optional) The reference to a user.
- api\_version (Optional)
- description: (Optional) A description for image.
- quarantine\_rule\_action: (Optional) These rules are used for quarantining suspected VMs. Target group is a required attribute. Empty inbound\_allow\_list will not allow anything into target group. Empty outbound allow list will allow everything from target group.
- quarantine\_rule\_outbound\_allow\_list: (Optional)
- quarantine\_rule\_target\_group\_default\_internal\_policy: (Optional) Default policy for communication within target group.
- quarantine\_rule\_target\_group\_peer\_specification\_type: (Optional) Way to identify the object for which rule is applied.
- quarantine\_rule\_target\_group\_filter\_kind\_list: (Optional) List of kinds associated with this filter.
- quarantine\_rule\_target\_group\_filter\_type: (Optional) The type of the filter being used.
- quarantine\_rule\_target\_group\_filter\_params: (Optional) A list of category key and list of values.
- quarantine\_rule\_inbound\_allow\_list: (Optional)
- app\_rule\_action: (Optional) These rules govern what flows are allowed. Target group is a required attribute. Empty inbound\_allow\_list will not anything into target group. Empty outbound\_allow\_list will allow everything from target group.
- app rule outbound allow list: (Optional)
- app\_rule\_target\_group\_default\_internal\_policy: (Optional) Default policy for communication within target group.
- app\_rule\_target\_group\_peer\_specification\_type: (Optional) Way to identify the object for which rule is applied.
- app\_rule\_target\_group\_filter\_kind\_list: (Optional) List of kinds associated with this filter.

- app\_rule\_target\_group\_filter\_type: (Optional) The type of the filter being used.
- app\_rule\_target\_group\_filter\_params: (Optional) A list of category key and list of values.
- app\_rule\_inbound\_allow\_list: (Optional)
- isolation\_rule\_action: (Optional) These rules are used for environmental isolation.
- app\_rule\_inbound\_allow\_list: (Optional)
- isolation\_rule\_first\_entity\_filter\_kind\_list: (Optional) List of kinds associated with this filter.
- isolation\_rule\_first\_entity\_filter\_type: (Optional) The type of the filter being used.
- isolation\_rule\_first\_entity\_filter\_params: (Optional) A list of category key and list of values.
- isolation\_rule\_second\_entity\_filter\_kind\_list: (Optional) List of kinds associated with this filter.
- isolation\_rule\_second\_entity\_filter\_type: (Optional) The type of the filter being used.
- isolation\_rule\_second\_entity\_filter\_params: (Optional) A list of category key and list of values.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when image was last updated.
- UUID: image UUID.
- creation\_time: UTC date and time in RFC-3339 format when image was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: image name.

### » Categories

The categories attribute supports the following:

- name: the key name.
- value: value of the key.

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, cluster\_reference, attributes supports the following:

- kind: The kind name (Default value: project).
- name: the name.
- uuid: the UUID.

### » Version

The version attribute supports the following:

- product\_name: Name of the producer/distribution of the image. For example windows or red hat.
- product\_version: Version string for the disk image.

See detailed information in Nutanix Security Rules.

# » nutanix\_cluster

Describes Clusters

# » Example Usage

```
data "nutanix_cluster" "cluster" {
   cluster_id = "<YOUR-CLUSTER-ID>"
}`
```

### » Argument Reference

The following arguments are supported:

• cluster\_id: Represents clusters uuid

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when image was last updated.
- uuid: image uuid.
- creation\_time: UTC date and time in RFC-3339 format when image was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: image name.

### » Categories

The categories attribute supports the following:

- name: the key name.
- value: value of the key.

### » Attribute Reference

The following attributes are exported:

- name: The name for the image.
- categories: Categories for the image.
- project\_reference: The reference to a project.
- owner\_reference: The reference to a user.
- availability\_zone\_reference: The reference to a availability\_zone.
- api\_version The API version.
- description: A description for image.
- metadata: The image kind metadata.
- state: The state of the cluster entity.
- gpu\_driver\_version: GPU driver version.
- client\_auth: Client authentication config.
- authorized\_piblic\_key\_list: List of valid ssh keys for the cluster.
- software\_map\_ncc: Map of software on the cluster with software type as the key.
- software\_map\_nos: Map of software on the cluster with software type as the key.
- encryption\_status: Cluster encryption status.
- ssl\_key\_type: SSL key type. Key types with RSA\_2048, ECDSA\_256 and ECDSA\_384 are supported for key generation and importing.
- ssl\_key\_signing\_info: Customer information used in Certificate Signing Request for creating digital certificates.
- ssl\_key\_expire\_datetime: UTC date and time in RFC-3339 format when the key expires
- service\_list: Array of enabled cluster services. For example, a cluster can function as both AOS and cloud data gateway. 'AOS': Regular Prism Element 'PRISM\_CENTRAL': Prism Central 'CLOUD\_DATA\_GATEWAY': Cloud backup and DR gateway 'AFS': Cluster for file server 'WITNESS': Witness cluster 'XI\_PORTAL': Xi cluster.
- supported\_information\_verbosity: Verbosity level settings for populating support information. 'Nothing': Send nothing 'Basic': Send basic information skip core dump and hypervisor stats information 'BasicPlusCoreDump': Send basic and core dump information 'All': Send all information (Default value: BASIC PLUS CORE DUMP)

- certification\_signing\_info: Customer information used in Certificate Signing Request for creating digital certificates.
- operation\_mode: Cluster operation mode. 'NORMAL': Cluster is operating normally. 'READ\_ONLY': Cluster is operating in read only mode. 'STAND\_ALONE': Only one node is operational in the cluster. This is valid only for single node or two node clusters. 'SWITCH\_TO\_TWO\_NODE': Cluster is moving from single node to two node cluster. 'OVERRIDE': Valid only for single node cluster. If the user wants to run vms on a single node cluster in read only mode, he can set the cluster peration mode to override. Writes will be allowed in override mode.
- ca\_certificate\_list: Zone name used in value of TZ environment variable.
- enabled feature list: Array of enabled features.
- is available: Indicates if cluster is available to contact. (Readonly)
- build: Cluster build details.
- timezone: Zone name used in value of TZ environment variable.
- cluster\_arch: Cluster architecture. (Readonly, Options: Options: X86 64, PPC64LE)
- management\_server\_list: List of cluster management servers. (Readonly)
- masquerading\_port: Port used together with masquerading\_ip to connect to the cluster.
- masquerading\_ip: The cluster NAT'd or proxy IP which maps to the cluster local IP.
- external ip: The local IP of cluster visible externally.
- http\_proxy\_list: List of proxies to connect to the service centers.
- smtp\_server\_type: SMTP Server type.
- smtp\_server\_email\_address: SMTP Server Email Address.
- smtp\_server\_credentials: SMTP Server Credentials.
- smtp server proxy type list: SMTP Server Proxy Type List
- smtp server address: SMTP Server Address.
- ntp\_server\_ip\_list: The list of IP addresses or FQDNs of the NTP servers.
- external\_subnet: External subnet for cross server communication. The format is IP/netmask. (default 172.16.0.0/255.240.0.0)
- external\_data\_services\_ip: The cluster IP address that provides external entities access to various cluster data services.
- internal\_subnet: The internal subnet is local to every server its not visible outside.iSCSI requests generated internally within the appliance (by user VMs or VMFS) are sent to the internal subnet. The format is IP/netmask.
- domain\_server\_nameserver: The IP of the nameserver that can resolve the domain name. Must set when joining the domain.
- domain\_server\_name: Joined domain name. In 'put' request, empty name will unjoin the cluster from current domain.

- domain\_server\_credentials: Cluster domain credentials.
- nfs\_subnet\_whitelist: Comma separated list of subnets (of the form 'a.b.c.d/l.m.n.o') that are allowed to send NFS requests to this container. If not specified, the global NFS whitelist will be looked up for access permission. The internal subnet is always automatically considered part of the whitelist, even if the field below does not explicitly specify it. Similarly, all the hypervisor IPs are considered part of the whitelist. Finally, to permit debugging, all of the SVMs local IPs are considered to be implicitly part of the whitelist.
- name\_server\_ip\_list: The list of IP addresses of the name servers.
- http\_proxy\_whitelist: HTTP proxy whitelist.
- analysis\_vm\_efficiency\_map: Map of cluster efficiency which includes numbers of inefficient vms. The value is populated by analytics on PC. (Readonly)

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, attributes supports the following:

- kind: The kind name (Default value: project).
- name: the name.
- uuid: the uuid.

### » Version

The version attribute supports the following:

- product\_name: Name of the producer/distribution of the image. For example windows or red hat.
- product\_version: Version string for the disk image.

See detailed information in Nutanix Image.

# » nutanix clusters

Describes Clusters

### » Example Usage

data "nutanix\_clusters" "clusters" {}

No arguments are supported:

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when image was last updated.
- uuid: image UUID.
- creation\_time: UTC date and time in RFC-3339 format when image was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: image name.

### » Categories

The categories attribute supports the following:

- name: the key name.
- value: value of the key.

# » Attribute Reference

The following attributes are exported:

• entities: List of Clusters

# » Entities

The entities attribute element contains the followings attributes:

- name: The name for the image.
- categories: Categories for the image.
- project\_reference: The reference to a project.
- owner\_reference: The reference to a user.
- availability\_zone\_reference: The reference to a availability\_zone.
- api\_version The API version.
- description: A description for image.
- $\bullet\,$  metadata: The image kind metadata.
- state: The state of the cluster entity.
- gpu\_driver\_version: GPU driver version.

- client\_auth: Client authentication config.
- authorized\_piblic\_key\_list: List of valid ssh keys for the cluster.
- software\_map\_ncc: Map of software on the cluster with software type as the key.
- software\_map\_nos: Map of software on the cluster with software type as the key.
- encryption\_status: Cluster encryption status.
- ssl\_key\_type: SSL key type. Key types with RSA\_2048, ECDSA\_256 and ECDSA\_384 are supported for key generation and importing.
- ssl\_key\_signing\_info: Customer information used in Certificate Signing Request for creating digital certificates.
- ssl\_key\_expire\_datetime: UTC date and time in RFC-3339 format when the key expires
- service\_list: Array of enabled cluster services. For example, a cluster can function as both AOS and cloud data gateway. 'AOS': Regular Prism Element 'PRISM\_CENTRAL': Prism Central 'CLOUD\_DATA\_GATEWAY': Cloud backup and DR gateway 'AFS': Cluster for file server 'WITNESS': Witness cluster 'XI\_PORTAL': Xi cluster.
- supported\_information\_verbosity: Verbosity level settings for populating support information. 'Nothing': Send nothing 'Basic': Send basic information skip core dump and hypervisor stats information 'BasicPlusCoreDump': Send basic and core dump information 'All': Send all information (Default value: BASIC\_PLUS\_CORE\_DUMP)
- certification\_signing\_info: Customer information used in Certificate Signing Request for creating digital certificates.
- operation\_mode: Cluster operation mode. 'NORMAL': Cluster is operating normally. 'READ\_ONLY': Cluster is operating in read only mode. 'STAND\_ALONE': Only one node is operational in the cluster. This is valid only for single node or two node clusters. 'SWITCH\_TO\_TWO\_NODE': Cluster is moving from single node to two node cluster. 'OVERRIDE': Valid only for single node cluster. If the user wants to run vms on a single node cluster in read only mode, he can set the cluster peration mode to override. Writes will be allowed in override mode.
- ca\_certificate\_list: Zone name used in value of TZ environment variable.
- enabled\_feature\_list: Array of enabled features.
- is\_available: Indicates if cluster is available to contact. (Readonly)
- build: Cluster build details.
- timezone: Zone name used in value of TZ environment variable.
- cluster\_arch: Cluster architecture. (Readonly, Options: Options: X86\_64, PPC64LE)
- management\_server\_list: List of cluster management servers. (Read-only)
- masquerading\_port: Port used together with masquerading\_ip to con-

nect to the cluster.

- masquerading\_ip: The cluster NAT'd or proxy IP which maps to the cluster local IP.
- external\_ip: The local IP of cluster visible externally.
- http\_proxy\_list: List of proxies to connect to the service centers.
- smtp\_server\_type: SMTP Server type.
- smtp\_server\_email\_address: SMTP Server Email Address.
- smtp\_server\_credentials: SMTP Server Credentials.
- smtp\_server\_proxy\_type\_list: SMTP Server Proxy Type List
- smtp\_server\_address: SMTP Server Address.
- ntp\_server\_ip\_list: The list of IP addresses or FQDNs of the NTP
  servers.
- external\_subnet: External subnet for cross server communication. The format is IP/netmask. (default 172.16.0.0/255.240.0.0)
- external\_data\_services\_ip: The cluster IP address that provides external entities access to various cluster data services.
- internal\_subnet: The internal subnet is local to every server its not visible outside.iSCSI requests generated internally within the appliance (by user VMs or VMFS) are sent to the internal subnet. The format is IP/netmask.
- domain\_server\_nameserver: The IP of the nameserver that can resolve the domain name. Must set when joining the domain.
- domain\_server\_name: Joined domain name. In 'put' request, empty name will unjoin the cluster from current domain.
- domain\_server\_credentials: Cluster domain credentials.
- nfs\_subnet\_whitelist: Comma separated list of subnets (of the form 'a.b.c.d/l.m.n.o') that are allowed to send NFS requests to this container. If not specified, the global NFS whitelist will be looked up for access permission. The internal subnet is always automatically considered part of the whitelist, even if the field below does not explicitly specify it. Similarly, all the hypervisor IPs are considered part of the whitelist. Finally, to permit debugging, all of the SVMs local IPs are considered to be implicitly part of the whitelist.
- name\_server\_ip\_list: The list of IP addresses of the name servers.
- http\_proxy\_whitelist: HTTP proxy whitelist.
- analysis\_vm\_efficiency\_map: Map of cluster efficiency which includes numbers of inefficient vms. The value is populated by analytics on PC. (Readonly)

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, cluster reference, attributes supports the following:

• kind: - The kind name (Default value: project).

```
• name: - the name.
```

• UUID: - the UUID.

### » Version

The version attribute supports the following:

- product\_name: Name of the producer/distribution of the image. For example windows or red hat.
- product\_version: Version string for the disk image.

See detailed information in Nutanix Image.

# » nutanix\_virtual\_machine

Provides a Nutanix Virtual Machine resource to Create a virtual machine.

# » Example Usage

```
data "nutanix_clusters" "clusters" {}

resource "nutanix_virtual_machine" "vm1" {
   name = "test-dou"
   cluster_uuid = data.nutanix_clusters.clusters.entities.0.metadata.uuid

categories {
        name = "Environment"
        value = "Staging"
      }

   num_vcpus_per_socket = 1
   num_sockets = 1
   memory_size_mib = 2048
}
```

# » Argument Reference

The following arguments are supported:

- name: (Required) The name for the vm.
- cluster\_uuid: (Required) The UUID of the cluster.
- categories: (Optional) Categories for the vm.

- project\_reference: (Optional) The reference to a project.
- owner\_reference: (Optional) The reference to a user.
- availability\_zone\_reference: (Optional) The reference to a availability zone.
- description: (Optional) A description for vm.
- num\_vnuma\_nodes: (Optional) Number of vNUMA nodes. 0 means vNUMA is disabled.
- nic\_list: (Optional) Spec NICs attached to the VM.
- serial\_port\_list: (Optional) Serial Ports configured on the VM.
- guest\_os\_id: (Optional) Guest OS Identifier. For ESX, refer to VMware documentation link for the list of guest OS identifiers.
- power\_state: (Optional) The current or desired power state of the VM. (Options: ON, OFF)
- nutanix\_guest\_tools: (Optional) Information regarding Nutanix Guest Tools.
- ngt\_credentials: (Ooptional) Credentials to login server.
- ngt\_enabled\_capability\_list (Optional) Application names that are enabled.
- num\_vcpus\_per\_socket: (Optional) Number of vCPUs per socket.
- num\_sockets: (Optional) Number of vCPU sockets.
- gpu\_list: (Optional) GPUs attached to the VM.
- parent\_referece: (Optional) Reference to an entity that the VM cloned from.
- memory\_size\_mib: (Optional) Memory size in MiB.
- boot\_device\_order\_list: (Optional) Indicates the order of device types in which VM should try to boot from. If boot device order is not provided the system will decide appropriate boot device order.
- boot\_device\_disk\_address: (Optional) Address of disk to boot from.
- boot\_device\_mac\_address: (Optional) MAC address of nic to boot from
- hardware\_clock\_timezone: (Optional) VM's hardware clock timezone in IANA TZDB format (America/Los Angeles).
- guest\_customization\_cloud\_init\_user\_data: (Optional) The contents of the user\_data configuration for cloud-init. This can be formatted as YAML, JSON, or could be a shell script. The value must be base64 encoded.
- guest\_customization\_cloud\_init\_meta\_data (Optional) The contents of the meta\_data configuration for cloud-init. This can be formatted as YAML or JSON. The value must be base64 encoded.
- guest\_customization\_cloud\_init\_custom\_key\_values: (Optional) Generic key value pair used for custom attributes in cloud init.
- guest\_customization\_is\_overridable: (Optional) Flag to allow override of customization by deployer.
- guest\_customization\_sysprep: (Optional) VM guests may be customized at boot time using one of several different methods. Currently, cloud-init w/ ConfigDriveV2 (for Linux VMs) and Sysprep (for Windows

VMs) are supported. Only ONE OF sysprep or cloud\_init should be provided. Note that guest customization can currently only be set during VM creation. Attempting to change it after creation will result in an error. Additional properties can be specified. For example - in the context of VM template creation if \"override\_script\" is set to \"True\" then the deployer can upload their own custom script.

- guest\_customization\_sysrep\_custom\_key\_values: (Optional Generic key value pair used for custom attributes in sysrep.
- should\_fail\_on\_script\_failure: (Optional) Extra configs related to power state transition. Indicates whether to abort ngt shutdown/reboot if script fails.
- enable\_script\_exec: (Optional) Extra configs related to power state transition. Indicates whether to execute set script before ngt shutdown/reboot.
- power\_state\_mechanism: (Optional) Indicates the mechanism guiding the VM power state transition. Currently used for the transition to \"OFF\" state. Power state mechanism (ACPI/GUEST/HARD).
- vga\_console\_enabled: (Optional) Indicates whether VGA console should be enabled or not.
- disk\_list Disks attached to the VM.

### » Disk List

The disk list attribute supports the following:

- uuid: (Optional) The device ID which is used to uniquely identify this particular disk.
- disk\_size\_bytes (Optional) Size of the disk in Bytes.
- disk\_size\_mib Size of the disk in MiB. Must match the size specified
  in 'disk\_size\_bytes' rounded up to the nearest MiB when that field is
  present.
- device\_properties Properties to a device.
- data\_source\_reference Reference to a data source.
- volume\_group\_reference Reference to a volume group.

The disk\_size (the disk size\_mib and the disk\_size\_bytes attributes) is only honored by creating an empty disk. When you are creating from an image, the size is ignored and the disk becomes the size of the image from which it was cloned. In VM creation, you can't set either disk size\_mib or disk\_size\_bytes when you set data\_source\_reference but, you can update the disk\_size after creation (second apply).

# » Device Properties

The device properties attribute supports the following.

- device\_type: A Disk type (default: DISK).
- disk\_address: Address of disk to boot from.

### » Sysprep

The guest customization sysprep attribute supports the following:

- install\_type: (Optional) Whether the guest will be freshly installed using this unattend configuration, or whether this unattend configuration will be applied to a pre-prepared image. Default is \"PREPARED\".
- unattend\_xml: (Optional) Generic key value pair used for custom attributes.

### » Disk Address

The boot\_device\_disk\_address attribute supports the following:

- device\_index: (Optional) The index of the disk address.
- adapter\_type: (Optional) The adapter type of the disk address.

### » GPU List

The gpu\_list attribute supports the following:

- frame\_buffer\_size\_mib: (ReadOnly) GPU frame buffer size in MiB.
- vendor: (Optional) The vendor of the GPU.
- uuid: (ReadOnly) UUID of the GPU.
- name: (ReadOnly) Name of the GPU resource.
- pci\_address (ReadOnly) GPU {segment:bus:device:function} (sbdf) address if assigned.
- fraction (ReadOnly) Fraction of the physical GPU assigned.
- mode: (Optional) The mode of this GPU.
- num\_virtual\_display\_heads: (ReadOnly) Number of supported virtual display heads.
- guest\_driver\_version: (ReadOnly) Last determined guest driver version.
- device\_id: (Computed) The device ID of the GPU.

#### » Nutanix Guest Tools

The nutanix guest tools attribute supports the following:

- state: (Optional) Nutanix Guest Tools is enabled or not.
- ngt\_state: (Optional) Nutanix Guest Tools is enabled or not.

- iso\_mount\_state: (Optional) Desired mount state of Nutanix Guest Tools ISO.
- version: (ReadOnly) Version of Nutanix Guest Tools installed on the VM
- available\_version: (ReadOnly) Version of Nutanix Guest Tools available on the cluster.
- guest\_os\_version: (ReadOnly) Version of the operating system on the VM.
- vss\_snapshot\_capable: (ReadOnly) Whether the VM is configured to take VSS snapshots through NGT.
- is\_reachable: (ReadOnly) Communication from VM to CVM is active or not.
- vm\_mobility\_drivers\_installed: (ReadOnly) Whether VM mobility drivers are installed in the VM.

### » NIC List

The nic\_list attribute supports the following:

- nic\_type: The type of this NIC. Defaults to NORMAL\_NIC. (Options : NORMAL\_NIC , DIRECT\_NIC , NETWORK\_FUNCTION\_NIC).
- uuid: The NIC's UUID, which is used to uniquely identify this particular NIC. This UUID may be used to refer to the NIC outside the context of the particular VM it is attached to.
- model: The model of this NIC. (Options: VIRTIO, E1000).
- network\_function\_nic\_type: The type of this Network function NIC. Defaults to INGRESS. (Options: INGRESS, EGRESS, TAP).
- mac\_address: The MAC address for the adapter.
- ip\_endpoint\_list: IP endpoints for the adapter. Currently, IPv4 addresses are supported.
- network\_function\_chain\_reference: The reference to a network function chain.
- subnet\_uuid: The reference to a subnet.
- subnet\_name: The name of the subnet reference to.
- floating\_ip: The Floating IP associated with the vnic. (Only in nic\_list\_status)

### » Serial Port List

The serial\_port\_list attribute supports the following:

- index: Index of the serial port (int).
- is\_connected: Indicates whether the serial port connection is connected or not (true or false).

### » ip\_endpoint\_list

The following attributes are exported:

- ip: Address string.
- type: Address type. It can only be "ASSIGNED" in the spec. If no type is specified in the spec, the default type is set to "ASSIGNED". (Options : ASSIGNED , LEARNED)

### » Attributes Reference

The following attributes are exported:

- metadata: The vm kind metadata.
- api\_version The version of the API.
- state: The state of the vm.
- cluster\_name: The name of the cluster.
- host\_reference: Reference to a host.
- hypervisor\_type: The hypervisor type for the hypervisor the VM is hosted on.
- nic\_list\_status: Status NICs attached to the VM.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when vm was last updated.
- uuid: vm UUID.
- creation\_time: UTC date and time in RFC-3339 format when vm was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: vm name.

### » Categories

The categories attribute supports the following:

- name: the key name.
- value: value of the key.

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, network\_function\_chain\_reference, data\_source\_reference, volume\_group\_reference attributes supports the following:

- kind: The kind name (Default value: project)(Required).
- name: the name(Optional).
- uuid: the UUID(Required).

See detailed information in Nutanix Virtual Machine.

# » nutanix\_volume\_group

Provides a Nutanix Volume Group resource to Create a volume\_group.

# » Example Usage

# » Argument Reference

The following arguments are supported:

- name: (Required) The name for the volume\_group.
- categories: (Optional) Categories for the volume\_group.
- project\_reference: (Optional) The reference to a project.
- owner\_reference: (Optional) The reference to a user.
- api\_version (Optional) Version of the API.
- description: (Optional) A description for volume\_group.
- flash\_mode: (Optional) Flash Mode, if enabled all volume disks of the VG will be pinned to SSD tier.
- file\_system\_type: (Optional) File system to be used for volume.
- sharing\_status: (Optiional) Whether the volume group can be shared across multiple iSCSI initiators.
- attachment\_list: (Optional) VMs attached to volume group.
- disk\_list: (Optional) Volume group disk specification.
- iscsi\_target\_prefix: (Optional) iSCSI target prefix-name.

### » Disk List

The disk list attribute supports the following:

- vmdisk UUID: (Optional) The UUID of this volume disk.
- index: (Optional) Index of the volume disk in the group.
- data\_source\_reference: (Optional) Reference to a kind
- disk size mib: (Optional) Size of the disk in MiB.
- storage\_container\_UUID: (Optional) Container UUID on which to create the disk.

### » Attachment List

The attachment\_list attribute supports the following:

- vm\_reference: (Optional) Reference to a kind.
- iscsi\_initiator\_name: (Optional) Name of the iSCSI initiator of the workload outside Nutanix cluster.

### » Attributes Reference

The following attributes are exported:

- metadata: The volume\_group kind metadata.
- state: The state of the volume group.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when volume\_group was last updated.
- UUID: volume\_group UUID.
- creation\_time: UTC date and time in RFC-3339 format when volume\_group was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: volume\_group name.

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, cluster\_reference, attributes supports the following:

• kind: - The kind name (Default value: project)(Required).

```
name: - the name(Optional).UUID: - the UUID(Required).
```

Note:  $\mbox{vm\_reference}$  and  $\mbox{data\_source\_reference}$  don't support name argument.

See detailed information in Nutanix Volume Group.

# » nutanix\_subnet

Provides a resource to create a subnet based on the input parameters. A subnet is a block of IP addresses.

# » Example Usage

```
data "nutanix_clusters" "clusters" {
 metadata = {
    length = 2
}
output "cluster" {
  value = data.nutanix_clusters.clusters.entities.0.metadata.uuid
}
resource "nutanix_subnet" "next-iac-managed" {
  # What cluster will this VLAN live on?
  cluster_uuid = "${data.nutanix_clusters.clusters.entities.0.metadata.uuid}"
 # General Information
             = "next-iac-managed-example"
 name
 vlan id
           = 101
 subnet_type = "VLAN"
 # Managed L3 Networks
 # This bit is only needed if you intend to turn on IPAM
 prefix_length = 20
 default_gateway_ip = "10.5.80.1"
  subnet_ip
                    = "10.5.80.0"
 dhcp_domain_name_server_list = ["8.8.8.8", "4.2.2.2"]
  dhcp_domain_search_list = ["nutanix.com", "eng.nutanix.com"]
```

- metadata: (Required) The subnet kind metadata.
- availability\_zone\_reference: (Optional) The reference to a availability zone.
- cluster\_uuid: (Required) The UUID of the cluster.
- description: (Optional) A description for subnet.
- name: (Optional) Subnet name (Readonly).
- categories: (Optional) The categories of the resource.
- owner\_reference: (Optional) The reference to a user.
- project\_reference: (Optional) The reference to a project.
- vswitch\_name: (Optional).
- subnet\_type: (Optional).
- default\_gateway\_ip: (Optional) Default gateway IP address.
- prefix\_length: (Optional).
- subnet\_ip: (Optional) Subnet IP address.
- dhcp\_server\_address: (Optional) Host address.
- dhcp\_server\_address\_port: (Optional) Port Number.
- dhcp\_options: (Optional) Spec for defining DHCP options.
- dhcp\_domain\_search\_list: (Optional).
- vlan\_id: (Optional).
- network\_function\_chain\_reference: (Optional) The reference to a network\_function\_chain.

### » Attributes Reference

The following attributes are exported:

- metadata: The vm kind metadata.
- state: The state of the subnet.
- api\_version The version of the API.

#### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when subnet was last updated.
- uuid: The subnet UUID.
- creation\_time: UTC date and time in RFC-3339 format when subnet was created.
- spec\_version: Version number of the latest spec.
- spec hash: Hash of the spec. This will be returned from server.
- name: subnet name.

### » Categories

The categories attribute supports the following:

- name: the key name.
- value: value of the key.

#### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, network\_function\_chain\_reference, subnet\_reference.

attributes supports the following:

- kind: The kind name (Default value: project)(Required).
- name: the name(Optional).
- uuid: the UUID(Required).

Note: subnet\_reference does not support the attribute name

See detailed information in Nutanix Subnet.

# » nutanix\_image

Provides a Nutanix Image resource to Create a image.

# » Example Usage

# » Argument Reference

The following arguments are supported:

- name: (Required) The name for the image.
- categories: (Optional) Categories for the image.
- project\_reference: (Optional) The reference to a project.
- owner\_reference: (Optional) The reference to a user.
- availability\_zone\_reference: (Optional) The reference to a availability\_zone.

- description: (Optional) A description for image.
- architecture: (Optional) The supported CPU architecture for a disk image.
- checksum: (Optional) Checksum of the image. The checksum is used for image validation if the image has a source specified. For images that do not have their source specified the checksum is generated by the image service.
- image\_type: (Optional) The type of image.
- source\_uri: (Optional) The source URI points at the location of the source image which is used to create/update image.
- source\_path: (Optional) A local path to upload an image.
- version: (Optional) The image version.

### » Version

The version attribute supports the following:

- product\_name: (Optional) Name of the producer/distribution of the image. For example windows or red hat.
- product version: (Optional) Version string for the disk image.

### » Attributes Reference

The following attributes are exported:

- metadata: The image kind metadata.
- retrieval\_uri\_list: List of URIs where the raw image data can be accessed.
- size\_bytes: The size of the image in bytes.
- state: The state of the image.
- api\_version The version of the API.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when image was last updated.
- uuid: image UUID.
- creation\_time: UTC date and time in RFC-3339 format when image was created.
- spec\_version: Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: image name.

### » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, attributes supports the following:

- kind: The kind name (Default value: project)(Required).
- name: the name(Optional).
- uuid: the UUID(Required).

See detailed information in Nutanix Image.

# » nutanix category key

Provides a Nutanix Category key resource to Create a category key name.

# » Example Usage

```
resource "nutanix_category_key" "test"{
   name = "app-support-example"
   description = "App Support Category Key"
}
```

# » Argument Reference

The following arguments are supported:

- name: (Required) The name for the category key.
- description: (Optional) A description for category key.

### » Attributes Reference

The following attributes are exported:

- system\_defined: Specifying whether its a system defined category.
- api\_version (Optional) The version of the API.

See detailed information in Nutanix Image.

# » nutanix\_category\_value

Provides a Nutanix Category value resource to Create a category value.

# » Example Usage

```
resource "nutanix_category_key" "test-category-key"{
   name = "app-support-1"
   description = "App Support Category Key"
}

resource "nutanix_category_value" "test"{
   name = nutanix_category_key.test-category-key.id
   description = "Test Category Value"
   value = "test-value"
}
```

# » Argument Reference

The following arguments are supported:

- name: (Required) The category\_key name for the category value.
- value (Required) The value for the category value.
- description: (Optional) A description for category value.

### » Attributes Reference

The following attributes are exported:

- system\_defined: Specifying whether its a system defined category.
- api\_version (Optional) The version of the API.

See detailed information in Nutanix Image.

# » nutanix\_network\_security\_rule

Provides a Nutanix network security rule resource to Create a network security rule.

# » Example Usage

### » Isolation Rule Example

```
resource "nutanix_network_security_rule" "isolation" {
   name = "example-isolation-rule"
   description = "Isolation Rule Example"
```

```
isolation_rule_action = "APPLY"
    isolation_rule_first_entity_filter_kind_list = ["vm"]
    isolation_rule_first_entity_filter_type
                                                = "CATEGORIES_MATCH_ALL"
    isolation_rule_first_entity_filter_params {
       name = "Environment"
        values = ["Dev"]
    }
    isolation_rule_second_entity_filter_kind_list = ["vm"]
                                                = "CATEGORIES_MATCH_ALL"
    isolation_rule_second_entity_filter_type
    isolation_rule_second_entity_filter_params {
       name = "Environment"
       values = ["Production"]
   }
}
» App Rule Example with associated VMs.
data "nutanix_clusters" "clusters" {}
locals {
  cluster_uuid = [
    for cluster in data.nutanix_clusters.clusters.entities :
    cluster.metadata.uuid if cluster.service_list[0] != "PRISM_CENTRAL"
 ][0]
}
//Create categories.
resource "nutanix_category_key" "test-category-key" {
 name = "TIER-1"
 description = "TIER Category Key"
}
resource "nutanix_category_key" "USER" {
             = "user"
 description = "user Category Key"
}
resource "nutanix_category_value" "WEB" {
             = "${nutanix_category_key.test-category-key.id}"
  description = "WEB Category Value"
             = "WEB-1"
  value
```

```
}
resource "nutanix_category_value" "APP" {
             = "${nutanix_category_key.test-category-key.id}"
 description = "APP Category Value"
           = "APP-1"
  value
}
resource "nutanix_category_value" "DB" {
             = "${nutanix_category_key.test-category-key.id}"
 description = "DB Category Value"
             = "DB-1"
 value
}
resource "nutanix_category_value" "group" {
             = "${nutanix_category_key.USER.id}"
 description = "group Category Value"
          = "group-1"
 value
}
//Create a cirros image
resource "nutanix_image" "cirros-034-disk" {
             = "test-image-vm-create-flow"
  source_uri = "http://download.cirros-cloud.net/0.4.0/cirros-0.4.0-x86_64-disk.img"
 description = "heres a tiny linux image, not an iso, but a real disk!"
}
//APP-1 VM.
resource "nutanix_virtual_machine" "vm-app" {
 name
                      = "test-dou-vm-flow-APP-1"
 cluster_uuid
                      = local.cluster_uuid
 num_vcpus_per_socket = 1
 num_sockets
                     = 186
 memory_size_mib
 nic_list {
    subnet_uuid = "c56b535c-8aff-4435-ae85-78e64a07f76d"
  disk_list {
   data_source_reference = {
     kind = "image"
     uuid = nutanix_image.cirros-034-disk.id
    }
```

```
device_properties {
      disk_address = {
        device_index = 0
        adapter_type = "SCSI"
      device_type = "DISK"
   }
  }
  categories {
    name = "Environment"
    value = "Staging"
  categories {
    name = "TIER-1"
    value = nutanix_category_value.APP.id
}
#WEB-1 VM
resource "nutanix_virtual_machine" "vm-web" {
                       = "test-dou-vm-flow-WEB-1"
                       = local.cluster_uuid
  cluster_uuid
  num_vcpus_per_socket = 1
  num_sockets
                     = 186
  memory_size_mib
  nic_list {
    subnet_uuid = "c56b535c-8aff-4435-ae85-78e64a07f76d"
  }
  disk_list {
    data_source_reference = {
     kind = "image"
      uuid = nutanix_image.cirros-034-disk.id
    }
    device_properties {
      disk_address = {
        device_index = 0
        adapter_type = "SCSI"
      device_type = "DISK"
   }
  }
```

```
categories {
   name = "Environment"
   value = "Staging"
  categories {
   name = "TIER-1"
    value = nutanix_category_value.WEB.id
 }
}
#DB-1 VM
resource "nutanix_virtual_machine" "vm-db" {
                      = "test-dou-vm-flow-DB-1"
 name
 cluster_uuid
                      = local.cluster_uuid
 num_vcpus_per_socket = 1
 num_sockets
                     = 1
                     = 186
 memory_size_mib
 nic_list {
    subnet_uuid = "c56b535c-8aff-4435-ae85-78e64a07f76d"
 disk_list {
   data_source_reference = {
     kind = "image"
     uuid = nutanix_image.cirros-034-disk.id
   }
    device_properties {
     disk_address = {
       device_index = 0
       adapter_type = "SCSI"
      device_type = "DISK"
   }
 }
  categories {
   name = "Environment"
   value = "Staging"
  categories {
   name = "TIER-1"
```

```
value = nutanix_category_value.DB.id
 }
}
//Create Application Network Policy.
resource "nutanix_network_security_rule" "TEST-TIER" {
             = "RULE-1-TIERS"
  description = "rule 1 tiers"
  app_rule_action = "APPLY"
  app_rule_inbound_allow_list {
   peer_specification_type = "FILTER"
                        = "CATEGORIES MATCH ALL"
    filter type
   filter_kind_list
                         = ["vm"]
   filter_params {
      name = "${nutanix_category_key.test-category-key.id}"
      values = ["${nutanix_category_value.WEB.id}"]
    }
 }
  app_rule_target_group_default_internal_policy = "DENY_ALL"
  app_rule_target_group_peer_specification_type = "FILTER"
  app_rule_target_group_filter_type = "CATEGORIES_MATCH_ALL"
  app_rule_target_group_filter_kind_list = ["vm"]
  app_rule_target_group_filter_params {
   name = "${nutanix_category_key.test-category-key.id}"
    values = ["${nutanix_category_value.APP.id}"]
 }
  app_rule_target_group_filter_params {
   name = "${nutanix_category_key.USER.id}"
    values = ["${nutanix_category_value.group.id}"]
  app_rule_target_group_filter_params {
   name = "AppType"
    values = ["Default"]
 }
  app_rule_outbound_allow_list {
```

The following arguments are supported:

• name: - (Required) The name for the image.

peer\_specification\_type = "FILTER"

- categories: (Optional) Categories for the image.
- project\_reference: (Optional) The reference to a project.
- owner\_reference: (Optional) The reference to a user.
- description: (Optional) A description for image.
- quarantine\_rule\_action: (Optional) These rules are used for quarantining suspected VMs. Target group is a required attribute. Empty inbound\_allow\_list will not allow anything into target group. Empty outbound\_allow\_list will allow everything from target group.
- quarantine\_rule\_outbound\_allow\_list: (Optional)
- quarantine\_rule\_target\_group\_default\_internal\_policy: (Optional) Default policy for communication within target group.
- quarantine\_rule\_target\_group\_peer\_specification\_type: (Optional) Way to identify the object for which rule is applied.
- quarantine\_rule\_target\_group\_filter\_kind\_list: (Optional) List of kinds associated with this filter.
- quarantine\_rule\_target\_group\_filter\_type: (Optional) The type of the filter being used.
- quarantine\_rule\_target\_group\_filter\_params: (Optional) A list of category key and list of values.
- quarantine\_rule\_inbound\_allow\_list: (Optional)
- app\_rule\_action: (Optional) These rules govern what flows are allowed. Target group is a required attribute. Empty inbound\_allow\_list will not anything into target group. Empty outbound\_allow\_list will allow everything from target group.
- app\_rule\_outbound\_allow\_list: (Optional)
- app\_rule\_target\_group\_default\_internal\_policy: (Optional) Default policy for communication within target group.

- app\_rule\_target\_group\_peer\_specification\_type: (Optional) Way to identify the object for which rule is applied.
- app\_rule\_target\_group\_filter\_kind\_list: (Optional) List of kinds associated with this filter.
- app\_rule\_target\_group\_filter\_type: (Optional) The type of the filter being used.
- app\_rule\_target\_group\_filter\_params: (Optional) A list of category key and list of values.
- app\_rule\_inbound\_allow\_list: (Optional)
- isolation\_rule\_action: (Optional) These rules are used for environmental isolation.
- app\_rule\_inbound\_allow\_list: (Optional)
- isolation\_rule\_first\_entity\_filter\_kind\_list: (Optional) List of kinds associated with this filter.
- isolation\_rule\_first\_entity\_filter\_type: (Optional) The type of the filter being used.
- isolation\_rule\_first\_entity\_filter\_params: (Optional) A list of category key and list of values.
- isolation\_rule\_second\_entity\_filter\_kind\_list: (Optional) List of kinds associated with this filter.
- isolation\_rule\_second\_entity\_filter\_type: (Optional) The type of the filter being used.
- isolation\_rule\_second\_entity\_filter\_params: (Optional) A list of category key and list of values.

### » Attributes Reference

The following attributes are exported:

- metadata: The image kind metadata.
- retrieval\_uri\_list: List of URIs where the raw image data can be accessed.
- size\_bytes: The size of the image in bytes.
- state: The state of the Network Security Rule.
- api\_version The version of the API.

### » Metadata

The metadata attribute exports the following:

- last\_update\_time: UTC date and time in RFC-3339 format when image was last updated.
- UUID: image UUID.
- creation\_time: UTC date and time in RFC-3339 format when image was created.

- $\bullet\,$   $\mbox{\tt spec\_version:}$  Version number of the latest spec.
- spec\_hash: Hash of the spec. This will be returned from server.
- name: image name.

# » Reference

The project\_reference, owner\_reference, availability\_zone\_reference, cluster\_reference, attributes supports the following:

- kind: The kind name (Default value: project)(Required).
- name: the name(Optional).
- uuid: the UUID(Required).

See detailed information in Nutanix Image.