# » docker\_registry\_image

Reads the image metadata from a Docker Registry. Used in conjunction with the docker\_image resource to keep an image up to date on the latest available version of the tag.

# » Example Usage

```
data "docker_registry_image" "ubuntu" {
   name = "ubuntu:precise"
}

resource "docker_image" "ubuntu" {
   name = "${data.docker_registry_image.ubuntu.name}"
   pull_triggers = ["${data.docker_registry_image.ubuntu.sha256_digest}"]
}
```

# » Argument Reference

The following arguments are supported:

• name - (Required, string) The name of the Docker image, including any tags. e.g. alpine:latest

# » Attributes Reference

The following attributes are exported in addition to the above configuration:

• sha256\_digest (string) - The content digest of the image, as stored on the registry.

# » docker container

Manages the lifecycle of a Docker container.

# » Example Usage

```
# Start a container
resource "docker_container" "ubuntu" {
  name = "foo"
  image = "${docker_image.ubuntu.latest}"
```

```
# Find the latest Ubuntu precise image.
resource "docker_image" "ubuntu" {
  name = "ubuntu:precise"
}
```

# » Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker container.
- image (Required, string) The ID of the image to back this container. The easiest way to get this value is to use the docker\_image resource as is shown in the example above.
- command (Optional, list of strings) The command to use to start the container. For example, to run /usr/bin/myprogram -f baz.conf set the command to be ["/usr/bin/myprogram", "-f", "baz.conf"].
- entrypoint (Optional, list of strings) The command to use as the Entrypoint for the container. The Entrypoint allows you to configure a container to run as an executable. For example, to run /usr/bin/myprogram when starting a container, set the entrypoint to be ["/usr/bin/myprogram"].
- user (Optional, string) User used for run the first process. Format is user or user:group which user and group can be passed literally or by name.
- dns (Optional, set of strings) Set of DNS servers.
- dns\_opts (Optional, set of strings) Set of DNS options used by the DNS provider(s), see resolv.conf documentation for valid list of options.
- dns\_search (Optional, set of strings) Set of DNS search domains that are used when bare unqualified hostnames are used inside of the container.
- env (Optional, set of strings) Environment variables to set.
- labels (Optional, block) See Labels below for details.
- links (Optional, set of strings) Set of links for link based connectivity between containers that are running on the same host.

Warning The --link flag is a legacy feature of Docker. It may eventually be removed. It exposes *all* environment variables originating from Docker to any linked containers. This could have serious security implications if sensitive data is stored in them. See [the docker documentation][linkdoc] for more details.

• hostname - (Optional, string) Hostname of the container.

- domainname (Optional, string) Domain name of the container.
- restart (Optional, string) The restart policy for the container. Must be one of "no", "on-failure", "always", "unless-stopped".
- max\_retry\_count (Optional, int) The maximum amount of times to an attempt a restart when restart is set to "on-failure"
- working\_dir- (Optional, string) The working directory for commands to run in
- rm (Optional, bool) If true, then the container will be automatically removed after his execution. Terraform won't check this container after creation.
- read\_only (Optional, bool) If true, the container will be started as readonly.
- start (Optional, bool) If true, then the Docker container will be started after creation. If false, then the container is only created.
- attach (Optional, bool) If true attach to the container after its creation and waits the end of his execution.
- logs (Optional, bool) Save the container logs (attach must be enabled).
- must\_run (Optional, bool) If true, then the Docker container will be kept running. If false, then as long as the container exists, Terraform assumes it is successful.
- capabilities (Optional, block) See Capabilities below for details.
- mounts (Optional, set of blocks) See Mounts below for details.
- tmpfs (Optional, map) A map of container directories which should be replaced by tmpfs mounts, and their corresponding mount options.
- ports (Optional, block) See Ports below for details.
- host (Optional, block) See Extra Hosts below for details.
- privileged (Optional, bool) Run container in privileged mode.
- devices (Optional, bool) See Devices below for details.
- publish\_all\_ports (Optional, bool) Publish all ports of the container.
- volumes (Optional, block) See Volumes below for details.
- memory (Optional, int) The memory limit for the container in MBs.
- memory\_swap (Optional, int) The total memory limit (memory + swap) for the container in MBs. This setting may compute to -1 after terraform apply if the target host doesn't support memory swap, when that is the case docker will use a soft limitation.
- shm\_size (Optional, int) Size of /dev/shm in MBs.
- cpu\_shares (Optional, int) CPU shares (relative weight) for the container.
- cpu\_set (Optional, string) A comma-separated list or hyphen-separated range of CPUs a container can use, e.g. 0-1.
- log\_driver (Optional, string) The logging driver to use for the container. Defaults to "json-file".
- log\_opts (Optional, map of strings) Key/value pairs to use as options for the logging driver.
- network\_alias (Optional, set of strings) Network aliases of the container for user-defined networks only. Deprecated: use networks\_advanced in-

stead.

- network\_mode (Optional, string) Network mode of the container.
- networks (Optional, set of strings) Id of the networks in which the container is. *Deprecated:* use networks\_advanced instead.
- networks\_advanced (Optional, block) See Networks Advanced below for details. If this block has priority to the deprecated network\_alias and network properties.
- destroy\_grace\_seconds (Optional, int) If defined will attempt to stop
  the container before destroying. Container will be destroyed after n seconds or on successful stop.
- upload (Optional, block) See File Upload below for details.
- ulimit (Optional, block) See Ulimits below for details.
- pid\_mode (Optional, string) The PID (Process) Namespace mode for the container. Either container:<name|id> or host.
- userns\_mode (Optional, string) Sets the usernamespace mode for the container when usernamespace remapping option is enabled.
- healthcheck (Optional, block) See Healthcheck below for details.
- sysctls (Optional, map) A map of kernel parameters (sysctls) to set in the container.
- ipc\_mode (Optional, string) IPC sharing mode for the container. Possible values are: none, private, shareable, container: <name | id> or host.
- group\_add (Optional, set of strings) Add additional groups to run as.

### » Labels

labels is a block within the configuration that can be repeated to specify additional label name and value data to the container. Each labels block supports the following:

- label (Required, string) Name of the label
- value (Required, string) Value of the label

See 214 for Details.

#### » Capabilities

capabilities is a block within the configuration that allows you to add or drop linux capabilities. For more information about what capabilities you can add and drop please visit the docker run documentation.

- add (Optional, set of strings) list of linux capabilities to add.
- drop (Optional, set of strings) list of linux capabilities to drop.

#### Example:

```
resource "docker container" "ubuntu" {
```

```
name = "foo"
image = "${docker_image.ubuntu.latest}"

capabilities {
   add = ["ALL"]
   drop = ["SYS_ADMIN"]
}
```

#### » Mounts

mounts is a block within the configuration that can be repeated to specify the extra mount mappings for the container. Each mounts block is the Specification for mounts to be added to container and supports the following:

- target (Required, string) The container path.
- source (Optional, string) The mount source (e.g., a volume name, a host path)
- type (Required, string) The mount type: valid values are bind | volume | tmpfs.
- read\_only (Optional, string) Whether the mount should be read-only
- ${\tt bind\_options}$  (Optional, map) Optional configuration for the  ${\tt bind}$  type.
  - propagation (Optional, string) A propagation mode with the value.
- volume\_options (Optional, map) Optional configuration for the volume type.
  - no\_copy (Optional, string) Whether to populate volume with data from the target.
  - labels (Optional, map of key/value pairs) Adding labels.
  - driver\_options (Optional, map of key/value pairs) Options for the driver.
- tmpfs\_options (Optional, map) Optional configuration for the tmpf type.
  - size bytes (Optional, int) The size for the tmpfs mount in bytes.
  - mode (Optional, int) The permission mode for the tmpfs mount in an integer.

#### » Ports

ports is a block within the configuration that can be repeated to specify the port mappings of the container. Each ports block supports the following:

- internal (Required, int) Port within the container.
- external (Optional, int) Port exposed out of the container. If not given a free random port >= 32768 will be used.
- ip (Optional, string) IP address/mask that can access this port, default to 0.0.0.0

• protocol - (Optional, string) Protocol that can be used over this port, defaults to tcp.

#### » Extra Hosts

host is a block within the configuration that can be repeated to specify the extra host mappings for the container. Each host block supports the following:

- host (Required, string) Hostname to add.
- ${\tt ip}$  (Required, string) IP address this host name should resolve to.

This is equivalent to using the --add-host option when using the run command of the Docker CLI.

#### » Volumes

volumes is a block within the configuration that can be repeated to specify the volumes attached to a container. Each volumes block supports the following:

- from\_container (Optional, string) The container where the volume is coming from.
- host\_path (Optional, string) The path on the host where the volume is coming from.
- volume\_name (Optional, string) The name of the docker volume which should be mounted.
- container\_path (Optional, string) The path in the container where the volume will be mounted.
- read\_only (Optional, bool) If true, this volume will be readonly. Defaults to false.

One of from\_container, host\_path or volume\_name must be set.

# » File Upload

upload is a block within the configuration that can be repeated to specify files to upload to the container before starting it. Only one of content or content\_base64 can be set and at least one of them hast to be set. Each upload supports the following

- content (Optional, string, conflicts with content\_base64 & source) Literal string value to use as the object content, which will be uploaded as UTF-8-encoded text.
- content\_base64 (Optional, string, conflicts with content & source)
  Base64-encoded data that will be decoded and uploaded as raw bytes for
  the object content. This allows safely uploading non-UTF8 binary data,

but is recommended only for larger binary content such as the result of the base64encode interpolation function. See here for the reason.

- source (Optional, string, conflicts with content & content\_base64) A filename that references a file which will be uploaded as the object content. This allows for large file uploads that do not get stored in state.
- source\_hash (Optional, string) If using source, this will force an update if the file content has updated but the filename has not.
- file (Required, string) path to a file in the container.
- executable (Optional, bool) If true, the file will be uploaded with user executable permission. Defaults to false.

#### » Network advanced

networks\_advanced is a block within the configuration that can be repeated to specify advanced options for the container in a specific network. Each networks advanced supports the following:

- name (Required, string) The name of the network.
- aliases (Optional, set of strings) The network aliases of the container in the specific network.
- ipv4\_address (Optional, string) The IPV4 address of the container in the specific network.
- ipv6\_address (Optional, string) The IPV6 address of the container in the specific network.

### » Devices

devices is a block within the configuration that can be repeated to specify the devices exposed to a container. Each devices block supports the following:

- host\_path (Required, string) The path on the host where the device is located.
- container\_path (Optional, string) The path in the container where the device will be binded.
- permissions (Optional, string) The cgroup permissions given to the container to access the device. Defaults to rwm.

#### » Ulimits

ulimit is a block within the configuration that can be repeated to specify the extra ulimits for the container. Each ulimit block supports the following:

- name (Required, string)
- soft (Required, int)
- hard (Required, int)

#### » Healthcheck

healthcheck is a block within the configuration that can be repeated only once to specify the extra healthcheck configuration for the container. The healthcheck block is a test to perform to check that the container is healthy and supports the following:

- test (Required, list of strings) Command to run to check health. For example, to run curl -f http://localhost/health set the command to be ["CMD", "curl", "-f", "http://localhost/health"].
- interval (Optional, string) Time between running the check (ms|s|m|h). Default: 0s.
- timeout (Optional, string) Maximum time to allow one check to run (ms|s|m|h). Default: 0s.
- start\_period (Optional, string) Start period for the container to initialize before counting retries towards unstable (ms|s|m|h). Default: Os.
- retries (Optional, int) Consecutive failures needed to report unhealthy.
   Default: 0.

# » Attributes Reference

The following attributes are exported:

- exit\_code The exit code of the container if its execution is done (must\_run must be disabled).
- container\_logs The logs of the container if its execution is done (attach must be disabled).
- network\_data (Map of a block) The IP addresses of the container on each network. Key are the network names, values are the IP addresses.
  - ip\_address The IP address of the container.
  - ip\_prefix\_length The IP prefix length of the container.
  - gateway The network gateway of the container.
- bridge The network bridge of the container as read from its Network-Settings.
- ip\_address Deprecated: Use network\_data instead. The IP address of the container's first network it.
- ip\_prefix\_length Deprecated: Use network\_data instead. The IP prefix length of the container as read from its NetworkSettings.
- gateway Deprecated: Use network\_data instead. The network gateway of the container as read from its NetworkSettings.

### » Import

Docker containers can be imported using the long id, e.g. for a container named foo:

```
$ terraform import docker_container.foo $(docker inspect -f {{.ID}} foo)
[linkdoc] https://docs.docker.com/network/links/
```

# » docker\_image

Pulls a Docker image to a given Docker host from a Docker Registry.

This resource will *not* pull new layers of the image automatically unless used in conjunction with docker\_registry\_image data source to update the pull\_triggers field.

# » Example Usage

```
# Find the latest Ubuntu precise image.
resource "docker_image" "ubuntu" {
   name = "ubuntu:precise"
}

# Access it somewhere else with ${docker_image.ubuntu.latest}

** Dynamic image

data "docker_registry_image" "ubuntu" {
   name = "ubuntu:precise"
}

resource "docker_image" "ubuntu" {
   name = "${data.docker_registry_image.ubuntu.name}"
   pull_triggers = ["${data.docker_registry_image.ubuntu.sha256_digest}"]
}
```

# » Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker image, including any tags or SHA256 repo digests.
- keep\_locally (Optional, boolean) If true, then the Docker image won't be deleted on destroy operation. If this is false, it will delete the image from the docker local storage on destroy operation.

- pull\_triggers (Optional, list of strings) List of values which cause an
  image pull when changed. This is used to store the image digest from the
  registry when using the docker\_registry\_image data source to trigger
  an image update.
- pull\_trigger Deprecated, use pull\_triggers instead.

### » Attributes Reference

The following attributes are exported in addition to the above configuration:

• latest (string) - The ID of the image.

# » docker\_network

Manages a Docker Network. This can be used alongside docker\_container to create virtual networks within the docker environment.

# » Example Usage

```
# Create a new docker network
resource "docker_network" "private_network" {
  name = "my_network"
}
# Access it somewhere else with ${docker_network.private_network.name}
```

# » Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker network.
- labels (Optional, block) See Labels below for details.
- check\_duplicate (Optional, boolean) Requests daemon to check for networks with same name.
- driver (Optional, string) Name of the network driver to use. Defaults to bridge driver.
- options (Optional, map of strings) Network specific options to be used by the drivers.
- internal (Optional, boolean) Restrict external access to the network. Defaults to false.
- attachable (Optional, boolean) Enable manual container attachment to the network. Defaults to false.

- ingress (Optional, boolean) Create swarm routing-mesh network. Defaults to false.
- ipv6 (Optional, boolean) Enable IPv6 networking. Defaults to false.
- ipam\_driver (Optional, string) Driver used by the custom IP scheme of the network.
- ipam\_config (Optional, block) See IPAM config below for details.

#### » Labels

labels is a block within the configuration that can be repeated to specify additional label name and value data to the container. Each labels block supports the following:

- label (Required, string) Name of the label
- value (Required, string) Value of the label

See 214 for Details.

### » IPAM config

Configuration of the custom IP scheme of the network.

The ipam\_config block supports:

- subnet (Optional, string)
- ip\_range (Optional, string)
- gateway (Optional, string)
- aux\_address (Optional, map of string)

# » Attributes Reference

The following attributes are exported in addition to the above configuration:

- id (string)
- scope (string)

# » Import

Docker networks can be imported using the long id, e.g. for a network with the short id p73jelnrme5f:

\$ terraform import docker\_network.foo \$(docker network inspect -f {{.ID}} p73)

# » docker\_volume

Creates and destroys a volume in Docker. This can be used alongside docker\_container to prepare volumes that can be shared across containers.

# » Example Usage

```
# Creates a docker volume "shared_volume".
resource "docker_volume" "shared_volume" {
   name = "shared_volume"
}
```

# Reference the volume with \${docker\_volume.shared\_volume.name}

# » Argument Reference

The following arguments are supported:

- name (Optional, string) The name of the Docker volume (generated if not provided).
- labels (Optional, map of string/string key/value pairs) User-defined key/value metadata.
- driver (Optional, string) Driver type for the volume (defaults to local).
- driver\_opts (Optional, map of strings) Options specific to the driver.

### » Attributes Reference

The following attributes are exported in addition to the above configuration:

• mountpoint (string) - The mountpoint of the volume.

# » Import

Docker volume can be imported using the long id, e.g. for a volume with the short id ecae276c5:

```
$ terraform import docker_volume.foo $(docker volume inspect -f {{.ID}} eca)
```

# » docker\_config

Manages the configuration of a Docker service in a swarm.

# » Example Usage

### » Basic

```
# Creates a config
resource "docker_config" "foo_config" {
  name = "foo_config"
  data = "ewogICJzZXJIfQo="
}
```

## » Advanced

# » Dynamically set config with a template

In this example you can use the \${var.foo\_port} variable to dynamically set the \${port} variable in the foo.configs.json.tpl template and create the data of the foo\_config with the help of the base64encode interpolation function.

```
File foo.config.json.tpl
  "server": {
    "public_port": ${port}
}
File main.tf
# Creates the template in renders the variable
data "template_file" "foo_config_tpl" {
 template = "${file("foo.config.json.tpl")}"
 vars {
    port = "${var.foo_port}"
}
# Creates the config
resource "docker_config" "foo_config" {
 name = "foo_config"
 data = "${base64encode(data.template_file.foo_config_tpl.rendered)}"
}
```

# » Update config with no downtime

To update a config, Terraform will destroy the existing resource and create a replacement. To effectively use a docker\_config resource with a docker\_service resource, it's recommended to specify create\_before\_destroy in a lifecycle block. Provide a unique name attribute, for example with one of the interpolation functions unid or timestamp as shown in the example below. The reason is moby-35803.

```
resource "docker_config" "service_config" {
 name = "${var.service name}-config-${replace(timestamp(),":", ".")}"
 data = "${base64encode(data.template_file.service_config_tpl.rendered)}"
 lifecycle {
    ignore_changes
                          = ["name"]
    create_before_destroy = true
}
resource "docker_service" "service" {
  # ...
  configs = [
    {
      config_id = "${docker_config.service_config.id}"
      config_name = "${docker_config.service_config.name}"
      file_name
                  = "/root/configs/configs.json"
   },
 ]
}
```

# » Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker config.
- data (Required, string) The base64 encoded data of the config.

# » Attributes Reference

The following attributes are exported in addition to the above configuration:

• id (string)

# » Import

Docker config can be imported using the long id, e.g. for a config with the short id p73jelnrme5f:

\$ terraform import docker\_config.foo \$(docker config inspect -f {{.ID}} p73)

# » docker\_secret

Manages the secrets of a Docker service in a swarm.

# » Example Usage

```
» Basic
```

```
# Creates a secret
resource "docker_secret" "foo_secret" {
  name = "foo_secret"
  data = "ewogICJzZXJsaasIfQo="
}
```

### » Update secret with no downtime

To update a secret, Terraform will destroy the existing resource and create a replacement. To effectively use a docker\_secret resource with a docker\_service resource, it's recommended to specify create\_before\_destroy in a lifecycle block. Provide a unique name attribute, for example with one of the interpolation functions unid or timestamp as shown in the example below. The reason is moby-35803.

```
resource "docker_secret" "service_secret" {
 name = "${var.service_name}-secret-${replace(timestamp(),":", ".")}"
  data = "${base64encode(data.template_file.service_secret_tpl.rendered)}"
 lifecycle {
                          = ["name"]
    ignore_changes
    create_before_destroy = true
 }
}
resource "docker_service" "service" {
 # ...
 secrets = [
    {
      secret_id = "${docker_secret.service_secret.id}"
      secret name = "${docker secret.service secret.name}"
      file_name = "/root/configs/configs.json"
    },
```

ì.

# » Argument Reference

The following arguments are supported:

- name (Required, string) The name of the Docker secret.
- data (Required, string) The base64 encoded data of the secret.
- labels (Optional, block) See Labels below for details.

### » Labels

labels is a block within the configuration that can be repeated to specify additional label name and value data to the container. Each labels block supports the following:

- label (Required, string) Name of the label
- $\bullet\,$  value (Required, string) Value of the label

See 214 for Details.

## » Attributes Reference

The following attributes are exported in addition to the above configuration:

• id (string)

# » Import

Docker secret cannot be imported as the secret data, once set, is never exposed again.

# » docker\_service

This resource manages the lifecycle of a Docker service. By default, the creation, update and delete of services are detached.

With the Converge Config the behavior of the docker cli is imitated to guarantee that for example, all tasks of a service are running or successfully updated or to inform terraform that a service could not be updated and was successfully rolled back.

# » Example Usage

The following examples show the basic and advanced usage of the Docker Service resource assuming the host machine is already part of a Swarm.

#### » Basic

The following configuration starts a Docker Service with - the given image, - 1 replica - exposes the port 8080 in vip mode to the host machine - moreover, uses the container runtime

```
resource "docker_service" "foo" {
  name = "foo-service"

  task_spec {
    container_spec {
      image = "repo.mycompany.com:8080/foo-service:v1"
    }
}

endpoint_spec {
    ports {
      target_port = "8080"
    }
}
```

The following command is the equivalent:

\$ docker service create -d -p 8080 --name foo-service repo.mycompany.com:8080/foo-service:v

### » Advanced

The following configuration shows the full capabilities of a Docker Service. Currently, the Docker API 1.32 is implemented.

```
resource "docker_volume" "test_volume" {
   name = "tftest-volume"
}

resource "docker_config" "service_config" {
   name = "tftest-full-myconfig"
   data = "ewogICJwcmVmaXgiOiAiMTIzIgp9"
}

resource "docker_secret" "service_secret" {
```

```
name = "tftest-mysecret"
 data = "ewogICJrZXkiOiAiUVdFUlRZIgp9"
}
resource "docker_network" "test_network" {
 name = "tftest-network"
 driver = "overlay"
}
resource "docker_service" "foo" {
 name = "tftest-service-basic"
 task_spec {
    container_spec {
      image = "repo.mycompany.com:8080/foo-service:v1"
     labels {
       label = "foo.bar"
       value = "baz"
      }
      command = ["ls"]
           = ["-las"]
     hostname = "my-fancy-service"
      env {
       MYFOO = "BAR"
            = "/root"
      dir
      user = "root"
      groups = ["docker", "foogroup"]
     privileges {
       se_linux_context {
          disable = true
          user = "user-label"
         role = "role-label"
         type = "type-label"
          level = "level-label"
       }
      }
     read_only = true
     mounts = [
```

```
= "/mount/test"
    target
            = "${docker_volume.test_volume.name}"
    source
             = "volume"
    type
    read_only = true
    bind_options {
     propagation = "private"
 },
1
stop_signal = "SIGTERM"
stop_grace_period = "10s"
healthcheck {
       = ["CMD", "curl", "-f", "http://localhost:8080/health"]
 test
 interval = "5s"
 timeout = "2s"
 retries = 4
}
hosts {
 host = "testhost"
 ip = "10.0.1.0"
dns_config {
 nameservers = ["8.8.8.8"]
 search = ["example.org"]
 options = ["timeout:3"]
}
secrets = [
 {
              = "${docker_secret.service_secret.id}"
    secret_id
    secret_name = "${docker_secret.service_secret.name}"
    file_name = "/secrets.json"
               = "0"
   file_uid
                      = "0"
             file_gid
             file_mode = 0777
 },
]
configs = [
 {
```

```
config_id = "${docker_config.service_config.id}"
      config_name = "${docker_config.service_config.name}"
                = "/configs.json"
      file_name
    },
 ]
}
resources {
  limits {
    nano_cpus
                = 1000000
    memory_bytes = 536870912
    generic_resources {
     named_resources_spec = [
        "GPU=UUID1",
      discrete_resources_spec = [
        "SSD=3",
   }
  }
  reservation {
                = 1000000
    nano_cpus
    memory_bytes = 536870912
    generic_resources {
     named_resources_spec = [
        "GPU=UUID1",
      ]
      discrete_resources_spec = [
        "SSD=3",
   }
 }
}
restart_policy = {
  condition = "on-failure"
             = "3s"
  delay
 max_attempts = 4
  window
              = "10s"
}
```

```
placement {
    constraints = [
      "node.role==manager",
   prefs = [
      "spread=node.role.manager",
 force_update = 0
 runtime = "container"
 networks
            = ["${docker_network.test_network.id}"]
  log_driver {
   name = "json-file"
    options {
     max-size = "10m"
     max-file = "3"
   }
 }
}
mode {
 replicated {
   replicas = 2
}
update_config {
 parallelism
                   = 2
                   = "10s"
 delay
 failure_action = "pause"
                   = "5s"
 monitor
 max_failure_ratio = "0.1"
                   = "start-first"
  order
}
rollback_config {
 parallelism
                   = 2
                   = "5ms"
  delay
 failure_action
                   = "pause"
                   = "10h"
 monitor
 max_failure_ratio = "0.9"
                   = "stop-first"
  order
```

```
endpoint_spec {
  mode = "vip"

ports {
   name = "random"
  protocol = "tcp"
  target_port = "8080"
  published_port = "8080"
  publish_mode = "ingress"
  }
}
```

See also the TestAccDockerService\_full test or all the other tests for a complete overview.

# » Argument Reference

The following arguments are supported:

- auth (Optional, block) See Auth below for details.
- name (Required, string) The name of the Docker service.
- task\_spec (Required, block) See TaskSpec below for details.
- mode (Optional, block) See Mode below for details.
- update\_config (Optional, block) See UpdateConfig below for details.
- rollback\_config (Optional, block) See RollbackConfig below for details.
- endpoint\_spec (Optional, block) See EndpointSpec below for details.
- converge\_config (Optional, block) See Converge Config below for details.

#### » Auth

auth can be used additionally to the registry\_auth. If both properties are given the auth wins and overwrites the auth of the provider.

- server\_address (Required, string) The address of the registry server
- username (Optional, string) The username to use for authenticating to the registry. If this is blank, the DOCKER\_REGISTRY\_USER is also be checked.
- password (Optional, string) The password to use for authenticating to the registry. If this is blank, the DOCKER\_REGISTRY\_PASS is also be checked.

### » TaskSpec

task\_spec is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The task\_spec block is the user modifiable task configuration and supports the following:

- container\_spec (Required, block) See ContainerSpec below for details.
- resources (Optional, block) See Resources below for details.
- restart\_policy (Optional, block) See Restart Policy below for details.
- placement (Optional, block) See Placement below for details.
- force\_update (Optional, int) A counter that triggers an update even if no relevant parameters have been changed. See Docker Spec.
- runtime (Optional, string) Runtime is the type of runtime specified for the task executor. See Docker Runtime.
- networks (Optional, set of strings) Ids of the networks in which the container will be put in.
- log\_driver (Optional, block) See Log Driver below for details.

### » ContainerSpec

container\_spec is a block within the configuration that can be repeated only once to specify the mode configuration for the service. The container\_spec block is the spec for each container and supports the following:

- image (Required, string) The image used to create the Docker service.
- labels (Optional, block) See Labels below for details.
- command (Optional, list of strings) The command to be run in the image.
- args (Optional, list of strings) Arguments to the command.
- hostname (Optional, string) The hostname to use for the container, as a valid RFC 1123 hostname.
- env (Optional, map of string/string) A list of environment variables in the form VAR=value.
- dir (Optional, string) The working directory for commands to run in.
- user (Optional, string) The user inside the container.
- groups (Optional, list of strings) A list of additional groups that the container process will run as.
- privileges (Optional, block) See Privileges below for details.
- read\_only (Optional, bool) Mount the container's root filesystem as read only.
- mounts (Optional, set of blocks) See Mounts below for details.
- stop\_signal (Optional, string) Signal to stop the container.
- stop\_grace\_period (Optional, string) Amount of time to wait for the container to terminate before forcefully removing it (ms|s|m|h).
- healthcheck (Optional, block) See Healthcheck below for details.
- host (Optional, map of string/string) A list of hostname/IP mappings to add to the container's hosts file.

- ip (Required string) The ip
- host (Required string) The hostname
- dns config (Optional, block) See DNS Config below for details.
- secrets (Optional, set of blocks) See Secrets below for details.
- configs (Optional, set of blocks) See Configs below for details.
- isolation (Optional, string) Isolation technology of the containers running the service. (Windows only). Valid values are: default|process|hyperv

#### » Labels

labels is a block within the configuration that can be repeated to specify additional label name and value data to the container. Each labels block supports the following:

- label (Required, string) Name of the label
- value (Required, string) Value of the label

See 214 for Details.

### » Privileges

privileges is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The **privileges** block holds the security options for the container and supports the following:

- credential\_spec (Optional, block) For managed service account (Windows only)
  - file (Optional, string) Load credential spec from this file.
  - registry (Optional, string) Load credential spec from this value in the Windows registry.
- se\_linux\_context (Optional, block) SELinux labels of the container
  - disable (Optional, bool) Disable SELinux
  - user (Optional, string) SELinux user label
  - role (Optional, string) SELinux role label
  - type (Optional, string) SELinux type label
  - level (Optional, string) SELinux level label

#### » Mounts

mounts is a block within the configuration that can be repeated to specify the extra mount mappings for the container. Each mounts block is the Specification for mounts to be added to containers created as part of the service and supports the following:

• target - (Required, string) The container path.

- source (Optional, string) The mount source (e.g., a volume name, a host path)
- type (Required, string) The mount type: valid values are bind | volume | tmpfs.
- read\_only (Optional, string) Whether the mount should be read-only
- bind\_options (Optional, map) Optional configuration for the bind type.
- propagation (Optional, string) A propagation mode with the value.
  volume\_options (Optional, map) Optional configuration for the volume
  - type.

     no conv. (Ontional string) Whather to populate values with data
    - no\_copy (Optional, string) Whether to populate volume with data from the target.
    - labels (Optional, block) See Labels above for details.
    - driver\_config (Optional, map) The name of the driver to create the volume.
    - name (Optional, string) The name of the driver to create the volume.
    - options (Optional, map of key/value pairs) Options for the driver.
- tmpfs\_options (Optional, map) Optional configuration for the tmpf type.
  - size\_bytes (Optional, int) The size for the tmpfs mount in bytes.
  - mode (Optional, int) The permission mode for the tmpfs mount in an integer.

#### » Healthcheck

healthcheck is a block within the configuration that can be repeated only **once** to specify the extra healthcheck configuration for the containers of the service. The healthcheck block is a test to perform to check that the container is healthy and supports the following:

- test (Required, list of strings) Command to run to check health. For example, to run curl -f http://localhost/health set the command to be ["CMD", "curl", "-f", "http://localhost/health"].
- interval (Optional, string) Time between running the check (ms|s|m|h). Default: Os.
- timeout (Optional, string) Maximum time to allow one check to run (ms|s|m|h). Default: 0s.
- start\_period (Optional, string) Start period for the container to initialize before counting retries towards unstable (ms|s|m|h). Default: 0s.
- retries (Optional, int) Consecutive failures needed to report unhealthy.
   Default: 0.

### » DNS Config

dns\_config is a block within the configuration that can be repeated only **once** to specify the extra DNS configuration for the containers of the service. The dns config block supports the following:

- nameservers (Required, list of strings) The IP addresses of the name servers, for example, 8.8.8.8
- search (Optional, list of strings) A search list for host-name lookup.
- options (Optional, list of strings) A list of internal resolver variables to be modified, for example, debug, ndots:3

#### » Secrets

secrets is a block within the configuration that can be repeated to specify the extra mount mappings for the container. Each secrets block is a reference to a secret that will be exposed to the service and supports the following:

- secret\_id (Required, string) ConfigID represents the ID of the specific secret.
- secret\_name (Optional, string) The name of the secret that this references, but internally it is just provided for lookup/display purposes
- file\_name (Required, string) Represents the final filename in the filesystem. The specific target file that the secret data is written within the docker container, e.g. /root/secret/secret.json
- file\_uid (Optional, string) Represents the file UID. Defaults: 0
- file\_gid (Optional, string) Represents the file GID. Defaults: 0
- file\_mode (Optional, int) Represents the FileMode of the file. Defaults:
   0444

# » Configs

configs is a block within the configuration that can be repeated to specify the extra mount mappings for the container. Each configs is a reference to a secret that is exposed to the service and supports the following:

- config\_id (Required, string) ConfigID represents the ID of the specific config.
- config\_name (Optional, string) The name of the config that this references, but internally it is just provided for lookup/display purposes
- file\_name (Required, string) Represents the final filename in the filesystem. The specific target file that the config data is written within the docker container, e.g. /root/config/config.json
- file uid (Optional, string) Represents the file UID. Defaults: 0
- file\_gid (Optional, string) Represents the file GID. Defaults: 0
- file\_mode (Optional, int) Represents the FileMode of the file. Defaults: 0444

#### » Resources

resources is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The **resources** block represents the requirements which apply to each container created as part of the service and supports the following:

- limits (Optional, list of strings) Describes the resources which can be advertised by a node and requested by a task.
  - nano\_cpus (Optional, int) CPU shares in units of 1/1e9 (or 10<sup>-9)</sup> of the CPU. Should be at least 1000000
  - memory\_bytes (Optional, int) The amount of memory in bytes the container allocates
  - generic\_resources (Optional, map) User-defined resources can be either Integer resources (e.g, SSD=3) or String resources (e.g, GPU=UUID1)
  - named\_resources\_spec (Optional, set of string) The String
    resources, delimited by =
  - discrete\_resources\_spec (Optional, set of string) The Integer resources, delimited by =
- reservation (Optional, list of strings) An object describing the resources which can be advertised by a node and requested by a task.
  - nano\_cpus (Optional, int) CPU shares in units of 1/1e9 (or 10<sup>-9)</sup> of the CPU. Should be at least 1000000
  - memory\_bytes (Optional, int) The amount of memory in bytes the container allocates
  - generic\_resources (Optional, map) User-defined resources can be either Integer resources (e.g, SSD=3) or String resources (e.g, GPU=UUID1)
  - named\_resources\_spec (Optional, set of string) The String resources
  - discrete\_resources\_spec (Optional, set of string) The Integer resources

## » Restart Policy

restart\_policy is a block within the configuration that can be repeated only once to specify the mode configuration for the service. The restart\_policy block specifies the restart policy which applies to containers created as part of this service and supports the following:

- condition (Optional, string) Condition for restart: (none|on-failure|any)
- delay (Optional, string) Delay between restart attempts (ms|s|m|h)
- max\_attempts (Optional, string) Maximum attempts to restart a given container before giving up (default value is 0, which is ignored)
- window (Optional, string) The time window used to evaluate the restart policy (default value is 0, which is unbounded) (ms|s|m|h)

#### » Placement

placement is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The placement block specifies the placement preferences and supports the following:

- constraints (Optional, set of strings) An array of constraints. e.g.: node.role==manager
- prefs (Optional, set of string) Preferences provide a way to make the scheduler aware of factors such as topology. They are provided in order from highest to lowest precedence, e.g.: spread=node.role.manager
- platforms (Optional, set of) Platforms stores all the platforms that the service's image can run on
  - architecture (Required, string) The architecture, e.g., amd64
  - os (Required, string) The operation system, e.g., linux

### » Log Driver

log\_driver is a block within the configuration that can be repeated only once
to specify the extra log\_driver configuration for the containers of the service.
The log\_driver specifies the log driver to use for tasks created from this spec.
If not present, the default one for the swarm will be used, finally falling back to
the engine default if not specified. The block supports the following:

- name (Required, string) The logging driver to use. Either (none|json-file|syslog|journald|gelf|fl
- options (Optional, a map of strings and strings) The options for the logging driver, e.g.

```
options {
  awslogs-region = "us-west-2"
  awslogs-group = "dev/foo-service"
}
```

### » Mode

mode is a block within the configuration that can be repeated only **once** to specify the mode configuration for the service. The mode block supports the following:

• global - (Optional, bool) set it to true to run the service in the global mode

```
resource "docker_service" "foo" {
    ...
  mode {
     global = true
  }
```

```
• replicated - (Optional, map), which contains atm only the amount of
replicas

resource "docker_service" "foo" {
    ...
    mode {
        replicated {
            replicas = 2
        }
    }
    ...
}
```

**NOTE** on mode: if neither global nor replicated is specified, the service is started in replicated mode with 1 replica. A change of service mode is not possible. The service has to be destroyed an recreated in the new mode.

### » UpdateConfig and RollbackConfig

update\_config or rollback\_config is a block within the configuration that can be repeated only **once** to specify the extra update configuration for the containers of the service. The update\_config rollback\_config block supports the following:

- parallelism (Optional, int) The maximum number of tasks to be updated in one iteration simultaneously (0 to update all at once).
- delay (Optional, int) Delay between updates (ns|us|ms|s|m|h), e.g. 5s
- failure\_action (Optional, int) Action on update failure: pause | continue | rollback.
- monitor (Optional, int) Duration after each task update to monitor for failure (ns|us|ms|s|m|h)
- max\_failure\_ratio (Optional, string) The failure rate to tolerate during an update as float. Important: the floatneed to be wrapped in a string to avoid internal casting and precision errors.
- order (Optional, int) Update order either 'stop-first' or 'start-first'.

### » EndpointSpec

endpoint\_spec is a block within the configuration that can be repeated only
once to specify properties that can be configured to access and load balance a
service. The block supports the following:

• mode - (Optional, string) The mode of resolution to use for internal load balancing between tasks. (vip|dnsrr). Default: vip.

• ports - (Optional, block) See Ports below for details.

#### » Ports

ports is a block within the configuration that can be repeated to specify the port mappings of the container. Each ports block supports the following:

- name (Optional, string) A random name for the port.
- protocol (Optional, string) Protocol that can be used over this port: tcp|udp|sctp. Default: tcp.
- target\_port (Required, int) Port inside the container.
- published\_port (Required, int) The port on the swarm hosts. If not set the value of target\_port will be used.
- publish\_mode (Optional, string) Represents the mode in which the port is to be published: ingress|host

#### » Converge Config

converge\_config is a block within the configuration that can be repeated only once to specify the extra Converging configuration for the containers of the service. This is the same behavior as the docker cli. By adding this configuration, it is monitored with the given interval that, e.g., all tasks/replicas of a service are up and healthy

The converge\_config block supports the following:

- delay (Optional, string) Time between each the check to check docker endpoint (ms|s|m|h). For example, to check if all tasks are up when a service is created, or to check if all tasks are successfully updated on an update. Default: 7s.
- timeout (Optional, string) The timeout of the service to reach the desired state (s|m). Default: 3m.

### » Attributes Reference

The following attributes are exported in addition to the above configuration:

• id (string)

# » Import

Docker service can be imported using the long id, e.g. for a service with the short id 55ba873dd:

\$ terraform import docker\_service.foo \$(docker service inspect -f {{.ID}} 55b)