» openstack_blockstorage_snapshot_v2

Use this data source to get information about an existing snapshot.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the V2 Block Storage client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the snapshot.
- status (Optional) The status of the snapshot.
- volume_id (Optional) The ID of the snapshot's volume.
- most_recent (Optional) Pick the most recently created snapshot if there are multiple results.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- status See Argument Reference above.
- volume_id See Argument Reference above.
- description The snapshot's description.
- size The size of the snapshot.
- metadata The snapshot's metadata.

${\tt "openstack_blockstorage_snapshot_v3}$

Use this data source to get information about an existing snapshot.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the V3 Block Storage client. If omitted, the region argument of the provider is used.
- name (Optional) The name of the snapshot.
- status (Optional) The status of the snapshot.
- volume_id (Optional) The ID of the snapshot's volume.
- most_recent (Optional) Pick the most recently created snapshot if there are multiple results.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- status See Argument Reference above.
- volume_id See Argument Reference above.
- description The snapshot's description.
- size The size of the snapshot.
- metadata The snapshot's metadata.

» openstack_compute_availability_zones_v2

Use this data source to get a list of availability zones from OpenStack

» Example Usage

```
data "openstack_compute_availability_zones_v2" "zones" {}
```

» Argument Reference

- region (Optional) The region to fetch availability zones from, defaults to the provider's region
- state (Optional) The state of the availability zones to match, default ("available").

» Attributes Reference

id is set to hash of the returned zone list. In addition, the following attributes are exported:

• names - The names of the availability zones, ordered alphanumerically, that match the queried state

» openstack_compute_flavor_v2

Use this data source to get the ID of an available OpenStack flavor.

» Example Usage

```
data "openstack_compute_flavor_v2" "small" {
  vcpus = 1
  ram = 512
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used.
- flavor_id (Optional) The ID of the flavor. Conflicts with the name, min_ram and min_disk
- name (Optional) The name of the flavor. Conflicts with the flavor_id.
- min_ram (Optional) The minimum amount of RAM (in megabytes). Conflicts with the flavor_id.
- ram (Optional) The exact amount of RAM (in megabytes).
- min_disk (Optional) The minimum amount of disk (in gigabytes). Conflicts with the flavor_id.
- disk (Optional) The exact amount of disk (in gigabytes).

- vcpus (Optional) The amount of VCPUs.
- swap (Optional) The amount of swap (in gigabytes).
- rx_tx_factor (Optional) The rx_tx_factor of the flavor.

id is set to the ID of the found flavor. In addition, the following attributes are exported:

- extra_specs Key/Value pairs of metadata for the flavor.
- is_public Whether the flavor is public or private.

" openstack_compute_keypair_v2

Use this data source to get the ID and public key of an OpenStack keypair.

» Example Usage

```
data "openstack_compute_keypair_v2" "kp" {
  name = "sand"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used.
- name (Required) The unique name of the keypair.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- fingerprint The fingerprint of the OpenSSH key.
- public_key The OpenSSH-formatted public key of the keypair.

» openstack_containerinfra_cluster_v1

Use this data source to get the ID of an available OpenStack Magnum cluster.

» Example Usage

```
data "openstack_containerinfra_cluster_v1" "cluster_1" {
  name = "cluster_1"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 Container Infra client. If omitted, the region argument of the provider is used.
- name (Required) The name of the cluster.

» Attributes Reference

id is set to the ID of the found cluster. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- project_id The project of the cluster.
- user_id The user of the cluster.
- created_at The time at which cluster was created.
- updated_at The time at which cluster was updated.
- api_address COE API address.
- coe_version COE software version.
- cluster_template_id The UUID of the V1 Container Infra cluster template.
- create_timeout The timeout (in minutes) for creating the cluster.
- discovery_url The URL used for cluster node discovery.
- docker_volume_size The size (in GB) of the Docker volume.
- flavor The flavor for the nodes of the cluster.

- master_flavor The flavor for the master nodes.
- keypair The name of the Compute service SSH keypair.
- labels The list of key value pairs representing additional properties of the cluster.
- master_count The number of master nodes for the cluster.
- node_count The number of nodes for the cluster.
- master_addresses IP addresses of the master node of the cluster.
- node_addresses IP addresses of the node of the cluster.
- stack_id UUID of the Orchestration service stack.

» openstack_containerinfra_clustertemplate_v1

Use this data source to get the ID of an available OpenStack Magnum cluster template.

» Example Usage

```
data "openstack_containerinfra_clustertemplate_v1" "clustertemplate_1" {
  name = "clustertemplate_1"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 Container Infra client. If omitted, the region argument of the provider is used.
- name (Required) The name of the cluster template.

» Attributes Reference

id is set to the ID of the found cluster template. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- project_id The project of the cluster template.

- user_id The user of the cluster template.
- created_at The time at which cluster template was created.
- updated_at The time at which cluster template was updated.
- apiserver_port The API server port for the Container Orchestration Engine for this cluster template.
- coe The Container Orchestration Engine for this cluster template.
- cluster_distro The distro for the cluster (fedora-atomic, coreos, etc.).
- dns_nameserver Address of the DNS nameserver that is used in nodes of the cluster.
- docker_storage_driver Docker storage driver. Changing this updates the Docker storage driver of the existing cluster template.
- docker_volume_size The size (in GB) of the Docker volume.
- external_network_id The ID of the external network that will be used for the cluster.
- fixed_network The fixed network that will be attached to the cluster.
- fixed_subnet = The fixed subnet that will be attached to the cluster.
- flavor The flavor for the nodes of the cluster.
- master_flavor The flavor for the master nodes.
- floating_ip_enabled Indicates whether created cluster should create IP floating IP for every node or not.
- http_proxy The address of a proxy for receiving all HTTP requests and relay them.
- https_proxy The address of a proxy for receiving all HTTPS requests and relay them.
- image The reference to an image that is used for nodes of the cluster.
- insecure_registry The insecure registry URL for the cluster template.
- keypair_id The name of the Compute service SSH keypair.
- labels The list of key value pairs representing additional properties of the cluster template.
- master_lb_enabled Indicates whether created cluster should has a loadbalancer for master nodes or not.
- network_driver The name of the driver for the container network.
- no_proxy A comma-separated list of IP addresses that shouldn't be used in the cluster.

- public Indicates whether cluster template should be public.
- registry_enabled Indicates whether Docker registry is enabled in the cluster
- server_type The server type for the cluster template.
- tls_disabled Indicates whether the TLS should be disabled in the cluster.
- volume_driver The name of the driver that is used for the volumes of the cluster nodes.

» openstack_dns_zone_v2

Use this data source to get the ID of an available OpenStack DNS zone.

» Example Usage

```
data "openstack_dns_zone_v2" "zone_1" {
  name = "example.com"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 DNS client. A DNS client is needed to retrieve zone ids. If omitted, the region argument of the provider is used.
- name (Optional) The name of the zone.
- description (Optional) A description of the zone.
- email (Optional) The email contact for the zone record.
- status (Optional) The zone's status.
- ttl (Optional) The time to live (TTL) of the zone.
- type (Optional) The type of the zone. Can either be PRIMARY or SECONDARY.

» Attributes Reference

id is set to the ID of the found zone. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- email See Argument Reference above.
- type See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- status See Argument Reference above.
- attributes Attributes of the DNS Service scheduler.
- masters An array of master DNS servers. When type is SECONDARY.
- created_at The time the zone was created.
- updated_at The time the zone was last updated.
- transferred_at The time the zone was transferred.
- version The version of the zone.
- serial The serial number of the zone.
- pool_id The ID of the pool hosting the zone.
- project_id The project ID that owns the zone.

» openstack_fw_policy_v1

Use this data source to get firewall policy information of an available OpenStack firewall policy.

» Example Usage

```
data "openstack_fw_policy_v1" "policy" {
  name = "tf_test_policy"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve firewall policy ids. If omitted, the region argument of the provider is used.
- policy_id (Optional) The ID of the firewall policy.
- name (Optional) The name of the firewall policy.
- tenant_id (Optional) The owner of the firewall policy.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- policy_id See Argument Reference above.
- name See Argument Reference above.
- tenant_id See Argument Reference above.
- description The description of the firewall policy.
- audited The audit status of the firewall policy.
- shared The sharing status of the firewall policy.
- rules The array of one or more firewall rules that comprise the policy.

» openstack_identity_auth_scope_v3

Use this data source to get authentication information about the current auth scope in use. This can be used as self-discovery or introspection of the username or project name currently in use.

» Example Usage

```
data "openstack_identity_auth_scope_v3" "scope" {
  name = "my_scope"
}
```

» Argument Reference

- name (Required) The name of the scope. This is an arbitrary name which is only used as a unique identifier so an actual token isn't used as the ID.
- region (Optional) The region in which to obtain the V3 Identity client. A Identity client is needed to retrieve tokens IDs. If omitted, the region argument of the provider is used.

» Attributes Reference

id is set to the name given to the scope. In addition, the following attributes are exported:

- user_name The username of the scope.
- user_id The user ID the of the scope.
- user_domain_name The domain name of the user.
- user_domain_id The domain ID of the user.
- project_name The project name of the scope.
- project_id The project ID of the scope.
- project_domain_name The domain name of the project.

- project_domain_id The domain ID of the project.
- roles A list of roles in the current scope. See reference below.

The roles block contains:

- role_id The ID of the role.
- role_name The name of the role.

" openstack_identity_endpoint_v3

Use this data source to get the ID of an OpenStack endpoint.

Note: This usually requires admin privileges.

» Example Usage

```
data "openstack_identity_endpoint_v3" "endpoint_1" {
   service_name = "demo"
}
```

» Argument Reference

The following arguments are supported:

- service_id (Optional) The service id this endpoint belongs to.
- service_name (Optional) The service name of the endpoint.
- interface (Optional) The endpoint interface. Valid values are public, internal, and admin. Default value is public
- region (Optional) The region the endpoint is located in.

» Attributes Reference

id is set to the ID of the found endpoint. In addition, the following attributes are exported:

- service_id See Argument Reference above.
- service_name See Argument Reference above.
- interface See Argument Reference above.
- url The endpoint URL
- region The region the endpoint is located in.

» openstack_identity_group_v3

Use this data source to get the ID of an OpenStack group.

Note: This usually requires admin privileges.

» Example Usage

```
data "openstack_identity_group_v3" "admins" {
  name = "admins"
}
```

» Argument Reference

- name The name of the group.
- domain_id (Optional) The domain the group belongs to.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.

» Attributes Reference

id is set to the ID of the found group. In addition, the following attributes are exported:

- name See Argument Reference above.
- domain_id See Argument Reference above.
- region See Argument Reference above.

> openstack_identity_project_v3

Use this data source to get the ID of an OpenStack project.

» Example Usage

```
data "openstack_identity_project_v3" "project_1" {
  name = "demo"
}
```

» Argument Reference

The following arguments are supported:

- domain_id (Optional) The domain this project belongs to.
- enabled (Optional) Whether the project is enabled or disabled. Valid values are true and false.
- is_domain (Optional) Whether this project is a domain. Valid values are true and false.
- name (Optional) The name of the project.
- parent_id (Optional) The parent of this project.

» Attributes Reference

id is set to the ID of the found project. In addition, the following attributes are exported:

- description The description of the project.
- domain id See Argument Reference above.
- enabled See Argument Reference above.
- is_domain See Argument Reference above.
- name See Argument Reference above.
- parent_id See Argument Reference above.
- region The region the project is located in.

» openstack_identity_role_v3

Use this data source to get the ID of an OpenStack role.

» Example Usage

```
data "openstack_identity_role_v3" "admin" {
  name = "admin"
}
```

» Argument Reference

- name The name of the role.
- domain_id (Optional) The domain the role belongs to.

• region - (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used.

» Attributes Reference

id is set to the ID of the found role. In addition, the following attributes are exported:

- name See Argument Reference above.
- domain_id See Argument Reference above.
- region See Argument Reference above.

» openstack_identity_user_v3

Use this data source to get the ID of an OpenStack user.

» Example Usage

```
data "openstack_identity_user_v3" "user_1" {
  name = "user_1"
}
```

» Argument Reference

The following arguments are supported:

- description (Optional) A description of the user.
- default_project_id (Optional) The default project this user belongs to.
- domain_id (Optional) The domain this user belongs to.
- enabled (Optional) Whether the user is enabled or disabled. Valid values are true and false.
- idp_id (Optional) The identity provider ID of the user.
- name (Optional) The name of the user.
- password_expires_at (Optional) Query for expired passwords. See the OpenStack API docs for more information on the query format.
- protocol_id (Optional) The protocol ID of the user.
- unique_id (Optional) The unique ID of the user.

The following attributes are exported:

- default_project_id See Argument Reference above.
- domain_id See Argument Reference above.
- enabled See Argument Reference above.
- idp id See Argument Reference above.
- name See Argument Reference above.
- password_expires_at See Argument Reference above.
- protocol_id See Argument Reference above.
- region The region the user is located in.
- unique_id See Argument Reference above.

» openstack_images_image_v2

Use this data source to get the ID of an available OpenStack image.

» Example Usage

```
data "openstack_images_image_v2" "ubuntu" {
  name = "Ubuntu 16.04"
  most_recent = true

  properties = {
    key = "value"
  }
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Glance client. A Glance client is needed to create an Image that can be used with a compute instance. If omitted, the region argument of the provider is used.
- most_recent (Optional) If more than one result is returned, use the most recent image.
- name (Optional) The name of the image.
- owner (Optional) The owner (UUID) of the image.
- properties (Optional) a map of key/value pairs to match an image with. All specified properties must be matched.

- size_min (Optional) The minimum size (in bytes) of the image to return.
- size_max (Optional) The maximum size (in bytes) of the image to return.
- sort_direction (Optional) Order the results in either asc or desc.
- sort_key (Optional) Sort images based on a certain key. Defaults to name.
- tag (Optional) Search for images with a specific tag.
- visibility (Optional) The visibility of the image. Must be one of "public", "private", "community", or "shared". Defaults to "private".
- member_status (Optional) The status of the image. Must be one of "accepted", "pending", "rejected", or "all".

id is set to the ID of the found image. In addition, the following attributes are exported:

- checksum The checksum of the data associated with the image.
- created_at The date the image was created.
- container_format: The format of the image's container.
- disk_format: The format of the image's disk.
- file the trailing path after the glance endpoint that represent the location of the image or the path to retrieve it.
- metadata The metadata associated with the image. Image metadata allow for meaningfully define the image properties and tags. See https://docs.openstack.org/glance/latest/user/metadefs-concepts.html.
- min_disk_gb The minimum amount of disk space required to use the image.
- min_ram_mb The minimum amount of ram required to use the image.
- properties Freeform information about the image.
- protected Whether or not the image is protected.
- schema The path to the JSON-schema that represent the image or image
- size_bytes The size of the image (in bytes).
- tags The tags list of the image.
- updated_at The date the image was last updated.

» openstack_networking_floatingip_v2

Use this data source to get the ID of an available OpenStack floating IP.

» Example Usage

```
data "openstack_networking_floatingip_v2" "floatingip_1" {
  address = "192.168.0.4"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve floating IP ids. If omitted, the region argument of the provider is used.
- description (Optional) Human-readable description of the floating IP.
- address (Optional) The IP address of the floating IP.
- pool (Optional) The name of the pool from which the floating IP belongs to.
- port_id (Optional) The ID of the port the floating IP is attached.
- status status of the floating IP (ACTIVE/DOWN).
- fixed_ip (Optional) The specific IP address of the internal port which should be associated with the floating IP.
- tags (Optional) The list of floating IP tags to filter.
- tenant_id (Optional) The owner of the floating IP.

» Attributes Reference

id is set to the ID of the found floating IP. In addition, the following attributes are exported:

• all_tags - A set of string tags applied on the floating IP.

${\tt "openstack_networking_network_v2}$

Use this data source to get the ID of an available OpenStack network.

» Example Usage

```
data "openstack_networking_network_v2" "network" {
  name = "tf_test_network"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve networks ids. If omitted, the region argument of the provider is used.
- network_id (Optional) The ID of the network.
- name (Optional) The name of the network.
- description (Optional) Human-readable description of the network.
- status (Optional) The status of the network.
- external (Optional) The external routing facility of the network.
- matching_subnet_cidr (Optional) The CIDR of a subnet within the network.
- tenant_id (Optional) The owner of the network.
- availability_zone_hints (Optional) The availability zone candidates for the network.
- transparent_vlan (Optional) The VLAN transparent attribute for the network.
- tags (Optional) The list of network tags to filter.

» Attributes Reference

id is set to the ID of the found network. In addition, the following attributes are exported:

- admin_state_up (Optional) The administrative state of the network.
- name See Argument Reference above.
- description See Argument Reference above.
- region See Argument Reference above.
- external See Argument Reference above.
- shared (Optional) Specifies whether the network resource can be accessed by any tenant or not.
- availability_zone_hints (Optional) The availability zone candidates for the network.
- transparent_vlan See Argument Reference above.
- all_tags The set of string tags applied on the network.

» openstack_networking_router_v2

Use this data source to get the ID of an available OpenStack router.

» Example Usage

```
data "openstack_networking_router_v2" "router" {
  name = "router_1"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve router ids. If omitted, the region argument of the provider is used.
- router_id (Optional) The UUID of the router resource.
- name (Optional) The name of the router.
- description (Optional) Human-readable description of the router.
- admin_state_up (Optional) Administrative up/down status for the router (must be "true" or "false" if provided).
- distributed (Optional) Indicates whether or not to get a distributed router.
- status (Optional) The status of the router (ACTIVE/DOWN).
- tags (Optional) The list of router tags to filter.
- tenant_id (Optional) The owner of the router.

» Attributes Reference

id is set to the ID of the found router. In addition, the following attributes are exported:

- enable_snat The value that points out if the Source NAT is enabled on the router.
- external_network_id The network UUID of an external gateway for the router.
- availability_zone_hints The availability zone that is used to make router resources highly available.
- external_fixed_ip The external fixed IPs of the router.

The external_fixed_ip block supports:

- subnet_id- Subnet in which the fixed IP belongs to.
- ip_address The IP address to set on the router.

• all_tags - The set of string tags applied on the router.

» openstack_networking_secgroup_v2

Use this data source to get the ID of an available OpenStack security group.

» Example Usage

```
data "openstack_networking_secgroup_v2" "secgroup" {
  name = "tf_test_secgroup"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve security groups ids. If omitted, the region argument of the provider is used.
- secgroup_id (Optional) The ID of the security group.
- name (Optional) The name of the security group.
- description (Optional) Human-readable description the the subnet.
- tags (Optional) The list of security group tags to filter.
- tenant_id (Optional) The owner of the security group.

» Attributes Reference

id is set to the ID of the found security group. In addition, the following attributes are exported:

- name See Argument Reference above.
- description- See Argument Reference above.
- all_tags The set of string tags applied on the security group.
- region See Argument Reference above.

${\tt "openstack_networking_subnet_v2}$

Use this data source to get the ID of an available OpenStack subnet.

» Example Usage

```
data "openstack_networking_subnet_v2" "subnet_1" {
  name = "subnet_1"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve subnet ids. If omitted, the region argument of the provider is used.
- name (Optional) The name of the subnet.
- description (Optional) Human-readable description for the subnet.
- dhcp_enabled (Optional) If the subnet has DHCP enabled.
- dhcp_disabled (Optional) If the subnet has DHCP disabled.
- ip_version (Optional) The IP version of the subnet (either 4 or 6).
- ipv6_address_mode (Optional) The IPv6 address mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- ipv6_ra_mode (Optional) The IPv6 Router Advertisement mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- gateway_ip (Optional) The IP of the subnet's gateway.
- cidr (Optional) The CIDR of the subnet.
- subnet_id (Optional) The ID of the subnet.
- subnetpool_id (Optional) The ID of the subnetpool associated with the subnet.
- network_id (Optional) The ID of the network the subnet belongs to.
- tenant_id (Optional) The owner of the subnet.
- tags (Optional) The list of subnet tags to filter.

» Attributes Reference

id is set to the ID of the found subnet. In addition, the following attributes are exported:

- allocation_pools Allocation pools of the subnet.
- enable_dhcp Whether the subnet has DHCP enabled or not.
- dns_nameservers DNS Nameservers of the subnet.

- host_routes Host Routes of the subnet.
- region See Argument Reference above.
- all_tags A set of string tags applied on the subnet.

» openstack_networking_subnetpool_v2

Use this data source to get the ID of an available OpenStack subnetpool.

» Example Usage

```
data "openstack_networking_subnetpool_v2" "subnetpool_1" {
  name = "subnetpool_1"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to retrieve a subnetpool id. If omitted, the region argument of the provider is used.
- name (Optional) The name of the subnetpool.
- default_quota (Optional) The per-project quota on the prefix space that can be allocated from the subnetpool for project subnets.
- project_id (Optional) The owner of the subnetpool.
- prefixes (Optional) A list of subnet prefixes that are assigned to the subnetpool.
- $default_prefixlen$ (Optional) The size of the subnetpool default prefix length.
- min prefixlen (Optional) The size of the subnetpool min prefix length.
- max_prefixlen (Optional) The size of the subnetpool max prefix length.
- address_scope_id (Optional) The Neutron address scope that subnet-pools is assigned to.
- ip_version The IP protocol version.
- ${\tt shared}$ (Optional) Whether this subnetpool is shared across all projects.
- description (Optional) The human-readable description for the subnetpool.

- is_default (Optional) Whether the subnetpool is default subnetpool or not.
- tags (Optional) The list of subnetpool tags to filter.

id is set to the ID of the found subnetpool. In addition, the following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- default_quota See Argument Reference above.
- project_id See Argument Reference above.
- created_at The time at which subnetpool was created.
- updated_at The time at which subnetpool was created.
- prefixes See Argument Reference above.
- default_prefixlen See Argument Reference above.
- min_prefixlen See Argument Reference above.
- max_prefixlen See Argument Reference above.
- address_scope_id See Argument Reference above.
- ip_version -The IP protocol version.
- shared See Argument Reference above.
- description See Argument Reference above.
- is_default See Argument Reference above.
- revision_number The revision number of the subnetpool.
- all_tags The set of string tags applied on the subnetpool.

» openstack_networking_port_v2

Use this data source to get the ID of an available OpenStack port.

» Example Usage

```
data "openstack_networking_port_v2" "port_1" {
  name = "port_1"
}
```

» Argument Reference

• region - (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve port ids. If omitted, the region argument of the provider is used.

- project_id (Optional) The owner of the port.
- port_id (Optional) The ID of the port.
- name (Optional) The name of the port.
- description (Optional) Human-readable description of the port.
- admin_state_up (Optional) The administrative state of the port.
- network_id (Optional) The ID of the network the port belongs to.
- device_owner (Optional) The device owner of the port.
- mac_address (Optional) The MAC address of the port.
- device_id (Optional) The ID of the device the port belongs to.
- fixed_ip (Optional) The port IP address filter.
- status (Optional) The status of the port.
- security_group_ids (Optional) The list of port security group IDs to filter.
- tags (Optional) The list of port tags to filter.

id is set to the ID of the found port. In addition, the following attributes are exported:

- region See Argument Reference above.
- project_id See Argument Reference above.
- port_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- admin_state_up See Argument Reference above.
- network_id See Argument Reference above.
- device_owner See Argument Reference above.
- mac_address See Argument Reference above.
- device_id See Argument Reference above.
- allowed_address_pairs An IP/MAC Address pair of additional IP addresses that can be active on this port. The structure is described below.
- all_fixed_ips The collection of Fixed IP addresses on the port in the order returned by the Network v2 API.

- all_security_group_ids The set of security group IDs applied on the port.
- all_tags The set of string tags applied on the port.
- extra_dhcp_option An extra DHCP option configured on the port. The structure is described below.

The allowed_address_pairs attribute has fields below:

- ip_address The additional IP address.
- mac_address The additional MAC address.

The extra_dhcp_option attribute has fields below:

- name Name of the DHCP option.
- value Value of the DHCP option.
- ip_version IP protocol version

» openstack_networking_port_ids_v2

Use this data source to get a list of Openstack Port IDs matching the specified criteria.

» Example Usage

```
data "openstack_networking_port_ids_v2" "ports" {
  name = "port"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Neutron client. A Neutron client is needed to retrieve port ids. If omitted, the region argument of the provider is used.
- project_id (Optional) The owner of the port.
- name (Optional) The name of the port.
- description (Optional) Human-readable description of the port.
- admin_state_up (Optional) The administrative state of the port.
- network_id (Optional) The ID of the network the port belongs to.
- device_owner (Optional) The device owner of the port.

- mac_address (Optional) The MAC address of the port.
- device_id (Optional) The ID of the device the port belongs to.
- fixed_ip (Optional) The port IP address filter.
- status (Optional) The status of the port.
- security_group_ids (Optional) The list of port security group IDs to filter.
- tags (Optional) The list of port tags to filter.
- sort_key (Optional) Sort ports based on a certain key. Defaults to none.
- sort_direction (Optional) Order the results in either asc or desc. Defaults to none.

ids is set to the list of Openstack Port IDs.

» openstack_sharedfilesystem_share_v2

Use this data source to get the ID of an available Shared File System share.

» Example Usage

```
data "openstack_sharedfilesystem_share_v2" "share_1" {
  name = "share_1"
}
```

» Argument Reference

- name (Optional) The name of the share.
- description (Optional) The human-readable description for the share.
- project_id (Optional) The owner of the share.
- snapshot_id (Optional) The UUID of the share's base snapshot.
- share_network_id (Optional) The UUID of the share's share network.
- export_location_path (Optional) The export location path of the share. Available since Manila API version 2.35.

- metadata (Optional) One or more metadata key and value pairs as a dictionary of strings.
- status (Optional) A share status filter. A valid value is creating, error, available, deleting, error_deleting, manage_starting, manage_error, unmanage_starting, unmanage_error, unmanaged, extending, extending_error, shrinking, shrinking_error, or shrinking_possible_data_loss_error.
- is_public (Optional) The level of visibility for the share. length.

id is set to the ID of the found share. In addition, the following attributes are exported:

- name See Argument Reference above.
- description See Argument Reference above.
- project_id See Argument Reference above.
- snapshot_id See Argument Reference above.
- share_network_id See Argument Reference above.
- export_location_path See Argument Reference above.
- metadata See Argument Reference above.
- status See Argument Reference above.
- is_public See Argument Reference above.
- region The region in which to obtain the V2 Shared File System client.
- availability_zone The share availability zone.
- share_proto The share protocol.
- size The share size, in GBs.
- export_locations A list of export locations. For example, when a share server has more than one network interface, it can have multiple export locations.

» openstack_sharedfilesystem_sharenetwork_v2

Use this data source to get the ID of an available Shared File System share network.

» Example Usage

```
data "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
  name = "sharenetwork_1"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to read a share network. If omitted, the region argument of the provider is used.
- name (Optional) The name of the share network.
- description (Optional) The human-readable description of the share network.
- project_id (Optional) The owner of the share network.
- neutron_net_id (Optional) The neutron network UUID of the share network.
- neutron_subnet_id (Optional) The neutron subnet UUID of the share network.
- security_service_id (Optional) The security service IDs associated with the share network.
- network_type (Optional) The share network type. Can either be VLAN, VXLAN, GRE, or flat.
- segmentation id (Optional) The share network segmentation ID.
- cidr (Optional) The share network CIDR.
- ip_version (Optional) The IP version of the share network. Can either be 4 or 6.

» Attributes Reference

id is set to the ID of the found share network . In addition, the following attributes are exported:

- region See Argument Reference above.
- project_id The owner of the Share Network.
- name See Argument Reference above.
- description See Argument Reference above.
- neutron_net_id See Argument Reference above.
- neutron_subnet_id See Argument Reference above.
- security_service_id See Argument Reference above.
- network_type See Argument Reference above.
- segmentation_id See Argument Reference above.
- cidr See Argument Reference above.
- ip_version See Argument Reference above.
- security_service_ids The list of security service IDs associated with the share network.

» openstack_sharedfilesystem_snapshot_v2

Use this data source to get the ID of an available Shared File System snapshot.

» Example Usage

```
data "openstack_sharedfilesystem_snapshot_v2" "snapshot_1" {
  name = "snapshot_1"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Shared File System client.
- name (Optional) The name of the snapshot.
- description (Optional) The human-readable description of the snap-shot.
- project_id (Optional) The owner of the snapshot.
- status (Optional) A snapshot status filter. A valid value is available, error, creating, deleting, manage_starting, manage_error, unmanage_starting, unmanage_error or error_deleting.

» Attributes Reference

id is set to the ID of the found snapshot. In addition, the following attributes are exported:

- name See Argument Reference above.
- description See Argument Reference above.
- project_id See Argument Reference above.
- status See Argument Reference above.
- size The snapshot size, in GBs.
- share_id The UUID of the source share that was used to create the snapshot.
- share_proto The file system protocol of a share snapshot.
- share_size The share snapshot size, in GBs.

» openstack_blockstorage_volume_v1

Manages a V1 volume resource within OpenStack.

» Example Usage

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes). Changing this creates a new volume.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- availability_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- image_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- snapshot_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source_vol_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- volume_type (Optional) The type of volume to create. Changing this
 creates a new volume.

» Attributes Reference

The following attributes are exported:

• region - See Argument Reference above.

- size See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- availability_zone See Argument Reference above.
- image_id See Argument Reference above.
- source_vol_id See Argument Reference above.
- snapshot_id See Argument Reference above.
- metadata See Argument Reference above.
- volume_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.

» Import

Volumes can be imported using the id, e.g.

\$ terraform import openstack_blockstorage_volume_v1.volume_1 ea257959-eeb1-4c10-8d33-26f0409

» openstack_blockstorage_volume_v2

Manages a V2 volume resource within OpenStack.

» Example Usage

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes). Changing this creates a new volume.

- availability_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- consistency_group_id (Optional) The consistency group to place the volume in.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- image_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- snapshot_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source_replica (Optional) The volume ID to replicate with.
- source_vol_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- volume_type (Optional) The type of volume to create. Changing this
 creates a new volume.

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- availability_zone See Argument Reference above.
- image_id See Argument Reference above.
- source_vol_id See Argument Reference above.
- snapshot_id See Argument Reference above.
- metadata See Argument Reference above.
- volume_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.

» Import

Volumes can be imported using the id, e.g.

\$ terraform import openstack_blockstorage_volume_v2.volume_1 ea257959-eeb1-4c10-8d33-26f0409

» openstack_blockstorage_volume_attach_v2

This resource is experimental and may be removed in the future! Feedback is requested if you find this resource useful or if you find any problems with it.

Creates a general purpose attachment connection to a Block Storage volume using the OpenStack Block Storage (Cinder) v2 API. Depending on your Block Storage service configuration, this resource can assist in attaching a volume to a non-OpenStack resource such as a bare-metal server or a remote virtual machine in a different cloud provider.

This does not actually attach a volume to an instance. Please use the openstack_compute_volume_attach_v2 resource for that.

» Example Usage

```
resource "openstack_blockstorage_volume_v2" "volume_1" {
   name = "volume_1"
   size = 1
}

resource "openstack_blockstorage_volume_attach_v2" "va_1" {
   volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
   device = "auto"
   host_name = "devstack"
   ip_address = "192.168.255.10"
   initiator = "iqn.1993-08.org.debian:01:e9861fb1859"
   os_type = "linux2"
   platform = "x86_64"
}
```

» Argument Reference

The following arguments are supported:

• region - (Optional) The region in which to obtain the V2 Block Storage client. A Block Storage client is needed to create a volume attachment.

If omitted, the **region** argument of the provider is used. Changing this creates a new volume attachment.

- attach_mode (Optional) Specify whether to attach the volume as Read-Only (ro) or Read-Write (rw). Only values of ro and rw are accepted. If left unspecified, the Block Storage API will apply a default of rw.
- device (Optional) The device to tell the Block Storage service this volume will be attached as. This is purely for informational purposes. You can specify auto or a device such as /dev/vdc.
- host name (Required) The host to attach the volume to.
- initiator (Optional) The iSCSI initiator string to make the connection.
- ip_address (Optional) The IP address of the host_name above.
- multipath (Optional) Whether to connect to this volume via multipath.
- os_type (Optional) The iSCSI initiator OS type.
- platform (Optional) The iSCSI initiator platform.
- volume_id (Required) The ID of the Volume to attach to an Instance.
- wwpn (Optional) An array of wwpn strings. Used for Fibre Channel connections.
- wwnn (Optional) A wwnn name. Used for Fibre Channel connections.

» Attributes Reference

In addition to the above, the following attributes are exported:

- data This is a map of key/value pairs that contain the connection information. You will want to pass this information to a provisioner script to finalize the connection. See below for more information.
- driver_volume_type The storage driver that the volume is based on.
- mount_point_base A mount point base name for shared storage.

» Volume Connection Data

Upon creation of this resource, a data exported attribute will be available. This attribute is a set of key/value pairs that contains the information required to complete the block storage connection.

As an example, creating an iSCSI-based volume will return the following:

```
data.access_mode = rw
data.auth_method = CHAP
data.auth_password = xUhbGKQ8QCwKmHQ2
data.auth_username = Sphn5X4EoyFUUMYVYSA4
data.target_iqn = iqn.2010-10.org.openstack:volume-2d87ed25-c312-4f42-be1d-3b36b014561d
data.target_portal = 192.168.255.10:3260
data.volume_id = 2d87ed25-c312-4f42-be1d-3b36b014561d
```

This information can then be fed into a provisioner or a template shell script, where the final result would look something like:

```
iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --interface defaulting iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --login iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n node iscsiadm -m node -T ${self.data.target_iqn} --op update -n node -T ${self.data.ta
```

The contents of data will vary from each Block Storage service. You must have a good understanding of how the service is configured and how to make the appropriate final connection. However, if used correctly, this has the flexibility to be able to attach OpenStack Block Storage volumes to non-OpenStack resources.

» Import

It is not possible to import this resource.

ightarrow openstack_blockstorage_volume_v3

Manages a V3 volume resource within OpenStack.

» Example Usage

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the volume. If omitted, the region argument of the provider is used. Changing this creates a new volume.
- size (Required) The size of the volume to create (in gigabytes).
- enable_online_resize (Optional) When this option is set it allows extending attached volumes. Note: updating size of an attached volume requires Cinder support for version 3.42 and a compatible storage driver.
- availability_zone (Optional) The availability zone for the volume. Changing this creates a new volume.
- consistency_group_id (Optional) The consistency group to place the volume in.
- description (Optional) A description of the volume. Changing this updates the volume's description.
- image_id (Optional) The image ID from which to create the volume. Changing this creates a new volume.
- metadata (Optional) Metadata key/value pairs to associate with the volume. Changing this updates the existing volume metadata.
- name (Optional) A unique name for the volume. Changing this updates the volume's name.
- snapshot_id (Optional) The snapshot ID from which to create the volume. Changing this creates a new volume.
- source_replica (Optional) The volume ID to replicate with.
- source_vol_id (Optional) The volume ID from which to create the volume. Changing this creates a new volume.
- volume_type (Optional) The type of volume to create. Changing this
 creates a new volume.
- multiattach (Optional) Allow the volume to be attached to more than one Compute instance.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- size See Argument Reference above.

- name See Argument Reference above.
- description See Argument Reference above.
- availability_zone See Argument Reference above.
- image_id See Argument Reference above.
- source_vol_id See Argument Reference above.
- snapshot_id See Argument Reference above.
- metadata See Argument Reference above.
- volume_type See Argument Reference above.
- attachment If a volume is attached to an instance, this attribute will display the Attachment ID, Instance ID, and the Device as the Instance sees it.
- multiattach See Argument Reference above.

» Import

Volumes can be imported using the id, e.g.

\$ terraform import openstack_blockstorage_volume_v3.volume_1 ea257959-eeb1-4c10-8d33-26f0409

» openstack_blockstorage_volume_attach_v3

This resource is experimental and may be removed in the future! Feedback is requested if you find this resource useful or if you find any problems with it.

Creates a general purpose attachment connection to a Block Storage volume using the OpenStack Block Storage (Cinder) v3 API. Depending on your Block Storage service configuration, this resource can assist in attaching a volume to a non-OpenStack resource such as a bare-metal server or a remote virtual machine in a different cloud provider.

This does not actually attach a volume to an instance. Please use the openstack_compute_volume_attach_v3 resource for that.

» Example Usage

```
resource "openstack_blockstorage_volume_v3" "volume_1" {
   name = "volume_1"
   size = 1
}

resource "openstack_blockstorage_volume_attach_v3" "va_1" {
   volume_id = "${openstack_blockstorage_volume_v3.volume_1.id}"
   device = "auto"
   host name = "devstack"
```

```
ip_address = "192.168.255.10"
initiator = "iqn.1993-08.org.debian:01:e9861fb1859"
os_type = "linux2"
platform = "x86_64"
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V3 Block Storage client. A Block Storage client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- attach_mode (Optional) Specify whether to attach the volume as Read-Only (ro) or Read-Write (rw). Only values of ro and rw are accepted. If left unspecified, the Block Storage API will apply a default of rw.
- device (Optional) The device to tell the Block Storage service this volume will be attached as. This is purely for informational purposes. You can specify auto or a device such as /dev/vdc.
- host_name (Required) The host to attach the volume to.
- initiator (Optional) The iSCSI initiator string to make the connection.
- ip_address (Optional) The IP address of the host_name above.
- multipath (Optional) Whether to connect to this volume via multipath.
- os type (Optional) The iSCSI initiator OS type.
- platform (Optional) The iSCSI initiator platform.
- volume_id (Required) The ID of the Volume to attach to an Instance.
- wwpn (Optional) An array of wwpn strings. Used for Fibre Channel connections.
- wwnn (Optional) A wwnn name. Used for Fibre Channel connections.

» Attributes Reference

In addition to the above, the following attributes are exported:

- data This is a map of key/value pairs that contain the connection information. You will want to pass this information to a provisioner script to finalize the connection. See below for more information.
- driver volume type The storage driver that the volume is based on.

• mount_point_base - A mount point base name for shared storage.

» Volume Connection Data

Upon creation of this resource, a data exported attribute will be available. This attribute is a set of key/value pairs that contains the information required to complete the block storage connection.

As an example, creating an iSCSI-based volume will return the following:

```
data.access_mode = rw
data.auth_method = CHAP
data.auth_password = xUhbGKQ8QCwKmHQ2
data.auth_username = Sphn5X4EoyFUUMYVYSA4
data.target_iqn = iqn.2010-10.org.openstack:volume-2d87ed25-c312-4f42-be1d-3b36b014561d
data.target_portal = 192.168.255.10:3260
data.volume_id = 2d87ed25-c312-4f42-be1d-3b36b014561d
```

This information can then be fed into a provisioner or a template shell script, where the final result would look something like:

```
iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --interface defauliscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nodiscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nodiscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nodiscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --login
iscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nodiscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --op update -n nodiscsiadm -m node -T ${self.data.target_iqn} -p ${self.data.target_portal} --rescan
```

The contents of data will vary from each Block Storage service. You must have a good understanding of how the service is configured and how to make the appropriate final connection. However, if used correctly, this has the flexibility to be able to attach OpenStack Block Storage volumes to non-OpenStack resources.

» Import

It is not possible to import this resource.

$ightsymbol{"} m openstack_compute_flavor_v2$

Manages a V2 flavor resource within OpenStack.

» Example Usage

```
resource "openstack_compute_flavor_v2" "test-flavor" {
  name = "my-flavor"
  ram = "8096"
  vcpus = "2"
  disk = "20"

extra_specs = {
    "hw:cpu_policy" = "CPU-POLICY",
    "hw:cpu_thread_policy" = "CPU-THREAD-POLICY"
  }
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Flavors are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new flavor.
- name (Required) A unique name for the flavor. Changing this creates a new flavor.
- ram (Required) The amount of RAM to use, in megabytes. Changing this creates a new flavor.
- vcpus (Required) The number of virtual CPUs to use. Changing this creates a new flavor.
- disk (Required) The amount of disk space in gigabytes to use for the root (/) partition. Changing this creates a new flavor.
- swap (Optional) The amount of disk space in megabytes to use. If unspecified, the default is 0. Changing this creates a new flavor.
- rx_tx_factor (Optional) RX/TX bandwith factor. The default is 1. Changing this creates a new flavor.
- is_public (Optional) Whether the flavor is public. Changing this creates a new flavor.
- extra_specs (Optional) Key/Value pairs of metadata for the flavor.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- ram See Argument Reference above.
- vcpus See Argument Reference above.
- disk See Argument Reference above.
- swap See Argument Reference above.
- rx_tx_factor See Argument Reference above.
- is_public See Argument Reference above.
- extra_specs See Argument Reference above.

» Import

Flavors can be imported using the ID, e.g.

» openstack_compute_flavor_access_v2

Manages a project access for flavor V2 resource within OpenStack.

Note: You *must* have admin privileges in your OpenStack cloud to use this resource.

» Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = "my-project"
}

resource "openstack_compute_flavor_v2" "flavor_1" {
   name = "my-flavor"
   ram = "8096"
   vcpus = "2"
   disk = "20"
   is_public = false
}

resource "openstack_compute_flavor_access_v2" "access_1" {
```

```
tenant_id = "${openstack_identity_project_v3.project_1.id}"
flavor_id = "${openstack_compute_flavor_v2.flavor_1.id}"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used. Changing this creates a new flavor access.
- flavor_id (Required) The UUID of flavor to use. Changing this creates a new flavor access.
- tenant_id (Required) The UUID of tenant which is allowed to use the flavor. Changing this creates a new flavor access.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- flavor id See Argument Reference above.
- tenant_id See Argument Reference above.

» Import

This resource can be imported by specifying all two arguments, separated by a forward slash:

\$ terraform import openstack_compute_flavor_access_v2.access_1 <flavor_id>/<tenant_id>

» openstack_compute_floatingip_v2

Manages a V2 floating IP resource within OpenStack Nova (compute) that can be used for compute instances.

Please note that managing floating IPs through the OpenStack Compute API has been deprecated. Unless you are using an older OpenStack environment, it is recommended to use the openstack_networking_floatingip_v2 resource instead, which uses the OpenStack Networking API.

» Example Usage

```
resource "openstack_compute_floatingip_v2" "floatip_1" {
  pool = "public"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a floating IP that can be used with a compute instance. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- pool (Required) The name of the pool from which to obtain the floating IP. Changing this creates a new floating IP.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- pool See Argument Reference above.
- address The actual floating IP address itself.
- fixed_ip The fixed IP address corresponding to the floating IP.
- instance_id UUID of the compute instance associated with the floating IP.

» Import

Floating IPs can be imported using the id, e.g.

\$ terraform import openstack_compute_floatingip_v2.floatip_1 89c60255-9bd6-460c-822a-e2b959e

$ightsymbol{"} ightsymbol{"} openstack_compute_floatingip_associate_v2$

Associate a floating IP to an instance. This can be used instead of the floating_ip options in openstack_compute_instance_v2.

» Example Usage

» Automatically detect the correct network

```
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
}
resource "openstack_networking_floatingip_v2" "fip_1" {
 pool = "my_pool"
}
resource "openstack_compute_floatingip_associate_v2" "fip_1" {
  floating_ip = "${openstack_networking_floatingip_v2.fip_1.address}"
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
}
» Explicitly set the network to attach to
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
 name
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                = 3
 flavor_id
               = "my_key_pair_name"
  key_pair
  security_groups = ["default"]
 network {
   name = "my_network"
 network {
   name = "default"
 }
}
resource "openstack_networking_floatingip_v2" "fip_1" {
 pool = "my_pool"
resource "openstack_compute_floatingip_associate_v2" "fip_1" {
  floating_ip = "${openstack_networking_floatingip_v2.fip_1.address}"
```

```
instance_id = "${openstack_compute_instance_v2.instance_1.id}"
fixed_ip = "${openstack_compute_instance_v2.instance_1.network.1.fixed_ip_v4}"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new floatingip_associate.
- floating_ip (Required) The floating IP to associate.
- instance_id (Required) The instance to associte the floating IP with.
- fixed_ip (Optional) The specific IP address to direct traffic to.
- wait_until_associated (Optional) In cases where the OpenStack environment does not automatically wait until the association has finished, set this option to have Terraform poll the instance until the floating IP has been associated. Defaults to false.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- floating_ip See Argument Reference above.
- instance_id See Argument Reference above.
- fixed_ip See Argument Reference above.

» Import

This resource can be imported by specifying all three arguments, separated by a forward slash:

\$ terraform import openstack_compute_floatingip_associate_v2.fip_1 <floating_ip>/<instance_</pre>

» openstack_compute_instance_v2

Manages a V2 VM instance resource within OpenStack.

» Example Usage

» Basic Instance

```
resource "openstack_compute_instance_v2" "basic" {
                 = "basic"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                 = "3"
 flavor_id
              = "my_key_pair_name"
 key_pair
  security_groups = ["default"]
 metadata = {
    this = "that"
 network {
   name = "my_network"
}
» Instance With Attached Volume
resource "openstack_blockstorage_volume_v2" "myvol" {
 name = "myvol"
 size = 1
}
resource "openstack_compute_instance_v2" "myinstance" {
                 = "myinstance"
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
 flavor_id
                 = "3"
                 = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 network {
   name = "my_network"
 }
}
resource "openstack_compute_volume_attach_v2" "attached" {
  instance_id = "${openstack_compute_instance_v2.myinstance.id}"
  volume_id = "${openstack_blockstorage_volume_v2.myvol.id}"
}
```

» Boot From Volume

```
resource "openstack_compute_instance_v2" "boot-from-volume" {
                 = "boot-from-volume"
 flavor_id
                 = "3"
                 = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 block_device {
                         = "<image-id>"
   uuid
                         = "image"
   source_type
                         = 5
   volume_size
   boot_index
                         = 0
                     = "volume"
   destination_type
   delete_on_termination = true
 network {
   name = "my_network"
}
» Boot From an Existing Volume
resource "openstack_blockstorage_volume_v1" "myvol" {
          = "myvol"
 name
 size
          = 5
 image_id = "<image-id>"
resource "openstack_compute_instance_v2" "boot-from-volume" {
                = "bootfromvolume"
 name
                = "3"
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 block_device {
                         = "${openstack_blockstorage_volume_v1.myvol.id}"
   uuid
                         = "volume"
   source_type
   boot_index
                         = 0
                         = "volume"
   destination_type
   delete_on_termination = true
 network {
```

```
name = "my_network"
 }
}
» Boot Instance, Create Volume, and Attach Volume as a Block De-
vice
resource "openstack_compute_instance_v2" "instance_1" {
                = "instance_1"
 name
                = "<image-id>"
 image_id
                = "3"
 flavor_id
 key_pair = "my_key_pair_name"
 security_groups = ["default"]
 block_device {
   uuid
                         = "<image-id>"
                        = "image"
   source_type
   destination_type
                        = "local"
   boot_index
   delete_on_termination = true
 }
 block_device {
                         = "blank"
   source_type
   destination_type
                       = "volume"
   volume_size
                         = 1
   boot_index
   delete_on_termination = true
}
» Boot Instance and Attach Existing Volume as a Block Device
resource "openstack_blockstorage_volume_v2" "volume_1" {
 name = "volume_1"
 size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
 name
               = "instance_1"
                = "<image-id>"
 image_id
```

= "my_key_pair_name"

= "3"

security_groups = ["default"]

flavor_id

key_pair

```
block_device {
    uuid
                          = "<image-id>"
                         = "image"
    source_type
    destination_type
                         = "local"
   boot_index
   delete_on_termination = true
 }
 block_device {
                          = "${openstack_blockstorage_volume_v2.volume_1.id}"
   uuid
                          = "volume"
    source_type
                         = "volume"
    destination_type
   boot index
                          = 1
   delete_on_termination = true
}
» Instance With Multiple Networks
resource "openstack_networking_floatingip_v2" "myip" {
 pool = "my_pool"
}
resource "openstack_compute_instance_v2" "multi-net" {
                 = "multi-net"
 name
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
  image_id
                 = "3"
 flavor_id
 key_pair
                 = "my_key_pair_name"
 security_groups = ["default"]
 network {
   name = "my_first_network"
 network {
   name = "my_second_network"
}
resource "openstack_compute_floatingip_associate_v2" "myip" {
  floating_ip = "${openstack_networking_floatingip_v2.myip.address}"
  instance_id = "${openstack_compute_instance_v2.multi-net.id}"
  fixed_ip = "${openstack_compute_instance_v2.multi-net.network.1.fixed_ip_v4}"
}
```

» Instance With Personality

```
resource "openstack_compute_instance_v2" "personality" {
                 = "personality"
 image_id
                 = "ad091b52-742f-469e-8f3c-fd81cadf0743"
                = "3"
 flavor_id
           = "my_key_pair_name"
 key_pair
 security_groups = ["default"]
 personality {
   file = "/path/to/file/on/instance.txt"
   content = "contents of file"
 }
 network {
   name = "my_network"
}
```

» Instance with Multiple Ephemeral Disks

```
resource "openstack_compute_instance_v2" "multi-eph" {
                = "multi eph"
 name
                = "ad091b52-742f-469e-8f3c-fd81cadf0743"
 image_id
 flavor_id
                = "3"
 key_pair
                = "my_key_pair_name"
 security_groups = ["default"]
 block_device {
   boot_index
                        = 0
   delete_on_termination = true
   destination_type = "local"
                        = "image"
   source_type
                       = "<image-id>"
   uuid
 }
 block_device {
   boot_index
                        = -1
   delete_on_termination = true
   destination_type = "local"
   source_type
                        = "blank"
   volume_size
                       = 1
 }
 block_device {
```

```
boot_index = -1
delete_on_termination = true
destination_type = "local"
source_type = "blank"
volume_size = 1
}
```

» Instance with User Data (cloud-init)

user_data can come from a variety of sources: inline, read in from the file function, or the template_cloudinit_config resource.

» Argument Reference

}

The following arguments are supported:

- region (Optional) The region in which to create the server instance. If omitted, the region argument of the provider is used. Changing this creates a new server.
- name (Required) A unique name for the resource.
- image_id (Optional; Required if image_name is empty and not booting from a volume. Do not specify if booting from a volume.) The image ID of the desired image for the server. Changing this creates a new server.
- image_name (Optional; Required if image_id is empty and not booting from a volume. Do not specify if booting from a volume.) The name of the desired image for the server. Changing this creates a new server.
- flavor_id (Optional; Required if flavor_name is empty) The flavor ID of the desired flavor for the server. Changing this resizes the existing server.

- flavor_name (Optional; Required if flavor_id is empty) The name of the desired flavor for the server. Changing this resizes the existing server.
- user_data (Optional) The user data to provide when launching the instance. Changing this creates a new server.
- security_groups (Optional) An array of one or more security group names to associate with the server. Changing this results in adding/removing security groups from the existing server. *Note*: When attaching the instance to networks using Ports, place the security groups on the Port and not the instance.
- availability_zone (Optional) The availability zone in which to create the server. Changing this creates a new server.
- network (Optional) An array of one or more networks to attach to the instance. The network object structure is documented below. Changing this creates a new server.
- metadata (Optional) Metadata key/value pairs to make available from within the instance. Changing this updates the existing server metadata.
- config_drive (Optional) Whether to use the config_drive feature to configure the instance. Changing this creates a new server.
- admin_pass (Optional) The administrative password to assign to the server. Changing this changes the root password on the existing server.
- key_pair (Optional) The name of a key pair to put on the server. The key pair must already be created and associated with the tenant's account. Changing this creates a new server.
- block_device (Optional) Configuration of block devices. The block_device structure is documented below. Changing this creates a new server. You can specify multiple block devices which will create an instance with multiple disks. This configuration is very flexible, so please see the following reference for more information.
- scheduler_hints (Optional) Provide the Nova scheduler with hints on how the instance should be launched. The available hints are described below.
- personality (Optional) Customize the personality of an instance by defining one or more files and their contents. The personality structure is described below.
- stop_before_destroy (Optional) Whether to try stop instance gracefully before destroying it, thus giving chance for guest OS daemons to stop correctly. If instance doesn't stop within timeout, it will be destroyed anyway.

- force_delete (Optional) Whether to force the OpenStack instance to be forcefully deleted. This is useful for environments that have reclaim / soft deletion enabled.
- power_state (Optional) Provide the VM state. Only 'active' and 'shutoff' are supported values. *Note*: If the initial power_state is the shutoff
 the VM will be stopped immediately after build and the provisioners like
 remote-exec or files are not supported.
- vendor_options (Optional) Map of additional vendor-specific options. Supported options are described below.

The network block supports:

- uuid (Required unless port or name is provided) The network UUID to attach to the server. Changing this creates a new server.
- name (Required unless unid or port is provided) The human-readable name of the network. Changing this creates a new server.
- port (Required unless unid or name is provided) The port UUID of a network to attach to the server. Changing this creates a new server.
- fixed_ip_v4 (Optional) Specifies a fixed IPv4 address to be used on this network. Changing this creates a new server.
- fixed_ip_v6 (Optional) Specifies a fixed IPv6 address to be used on this network. Changing this creates a new server.
- access_network (Optional) Specifies if this network should be used for provisioning access. Accepts true or false. Defaults to false.

The block_device block supports:

- uuid (Required unless source_type is set to "blank") The UUID of the image, volume, or snapshot. Changing this creates a new server.
- source_type (Required) The source type of the device. Must be one of "blank", "image", "volume", or "snapshot". Changing this creates a new server.
- volume_size The size of the volume to create (in gigabytes). Required in the following combinations: source=image and destination=volume, source=blank and destination=local, and source=blank and destination=volume. Changing this creates a new server.
- boot_index (Optional) The boot index of the volume. It defaults to 0. Changing this creates a new server.
- destination_type (Optional) The type that gets created. Possible values are "volume" and "local". Changing this creates a new server.

- delete_on_termination (Optional) Delete the volume / block device upon termination of the instance. Defaults to false. Changing this creates a new server.
- device_type (Optional) The low-level device type that will be used. Most common thing is to leave this empty. Changing this creates a new server.
- disk_bus (Optional) The low-level disk bus that will be used. Most common thing is to leave this empty. Changing this creates a new server.

The scheduler hints block supports:

- group (Optional) A UUID of a Server Group. The instance will be placed into that group.
- different_host (Optional) A list of instance UUIDs. The instance will be scheduled on a different host than all other instances.
- same_host (Optional) A list of instance UUIDs. The instance will be scheduled on the same host of those specified.
- query (Optional) A conditional query that a compute node must pass in order to host an instance.
- target_cell (Optional) The name of a cell to host the instance.
- build_near_host_ip (Optional) An IP Address in CIDR form. The instance will be placed on a compute node that is in the same subnet.
- additional_properties (Optional) Arbitrary key/value pairs of additional properties to pass to the scheduler.

The personality block supports:

- file (Required) The absolute path of the destination file.
- content (Required) The contents of the file. Limited to 255 bytes.

The vendor options block supports:

• ignore_resize_confirmation - (Optional) Boolean to control whether to ignore manual confirmation of the instance resizing. This can be helpful to work with some OpenStack clouds which automatically confirm resizing of instances after some timeout.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- access_ip_v4 The first detected Fixed IPv4 address or the Floating IP.

- access_ip_v6 The first detected Fixed IPv6 address.
- metadata See Argument Reference above.
- security_groups See Argument Reference above.
- flavor_id See Argument Reference above.
- flavor_name See Argument Reference above.
- network/uuid See Argument Reference above.
- network/name See Argument Reference above.
- network/port See Argument Reference above.
- network/fixed_ip_v4 The Fixed IPv4 address of the Instance on that network.
- network/fixed_ip_v6 The Fixed IPv6 address of the Instance on that network.
- network/mac The MAC address of the NIC on that network.
- all_metadata Contains all instance metadata, even metadata not set by Terraform.

» Notes

» Multiple Ephemeral Disks

It's possible to specify multiple block_device entries to create an instance with multiple ephemeral (local) disks. In order to create multiple ephemeral disks, the sum of the total amount of ephemeral space must be less than or equal to what the chosen flavor supports.

The following example shows how to create an instance with multiple ephemeral disks:

```
resource "openstack_compute_instance_v2" "foo" {
                 = "terraform-test"
 security_groups = ["default"]
 block_device {
   boot index
   delete_on_termination = true
   destination_type = "local"
                        = "image"
   source_type
   uuid
                         = "<image uuid>"
 }
 block_device {
   boot_index
   delete_on_termination = true
   destination_type = "local"
                        = "blank"
    source_type
    volume_size
                         = 1
```

» Instances and Security Groups

When referencing a security group resource in an instance resource, always use the *name* of the security group. If you specify the ID of the security group, Terraform will remove and reapply the security group upon each call. This is because the OpenStack Compute API returns the names of the associated security groups and not their IDs.

Note the following example:

```
resource "openstack_networking_secgroup_v2" "sg_1" {
   name = "sg_1"
}

resource "openstack_compute_instance_v2" "foo" {
   name = "terraform-test"
   security_groups = ["${openstack_networking_secgroup_v2.sg_1.name}"]
}
```

» Instances and Ports

Neutron Ports are a great feature and provide a lot of functionality. However, there are some notes to be aware of when mixing Instances and Ports:

- In OpenStack environments prior to the Kilo release, deleting or recreating an Instance will cause the Instance's Port(s) to be deleted. One way of working around this is to taint any Port(s) used in Instances which are to be recreated. See here for further information.
- When attaching an Instance to one or more networks using Ports, place the security groups on the Port and not the Instance. If you place the security groups on the Instance, the security groups will not be applied upon creation, but they will be applied upon a refresh. This is a known OpenStack bug.

• Network IP information is not available within an instance for networks that are attached with Ports. This is mostly due to the flexibility Neutron Ports provide when it comes to IP addresses. For example, a Neutron Port can have multiple Fixed IP addresses associated with it. It's not possible to know which single IP address the user would want returned to the Instance's state information. Therefore, in order for a Provisioner to connect to an Instance via it's network Port, customize the connection information:

```
resource "openstack_networking_port_v2" "port_1" {
                 = "port 1"
 admin_state_up = "true"
 network_id = "0a1d0a27-cffa-4de3-92c5-9d3fd3f2e74d"
 security_group_ids = [
    "2f02d20a-8dca-49b7-b26f-b6ce9fddaf4f",
    "ca1e5ed7-dae8-4605-987b-fadaeeb30461",
 ]
}
resource "openstack_compute_instance_v2" "instance_1" {
 name = "instance_1"
 network {
   port = "${openstack_networking_port_v2.port_1.id}"
  connection {
                = "root"
    user
                = "${openstack_networking_port_v2.port_1.fixed_ip.0.ip_address}"
   private_key = "~/path/to/key"
 }
 provisioner "remote-exec" {
   inline = [
      "echo terraform executed > /tmp/foo",
    ]
 }
}
```

» Instances and Networks

Instances almost always require a network. Here are some notes to be aware of with how Instances and Networks relate:

- In scenarios where you only have one network available, you can create an instance without specifying a network block. OpenStack will automatically launch the instance on this network.
- If you have access to more than one network, you will need to specify a network with a **network** block. Not specifying a network will result in the following error:
- * openstack_compute_instance_v2.instance: Error creating OpenStack server: Expected HTTP response code [201 202] when accessing [POST https://example.com:8774/v2.1/set {"conflictingRequest": {"message": "Multiple possible networks found, use a Network ID to be
 - If you intend to use the openstack_compute_interface_attach_v2 resource, you still need to make sure one of the above points is satisfied. An instance cannot be created without a valid network configuration even if you intend to use openstack_compute_interface_attach_v2 after the instance has been created.

» openstack_compute_interface_attach_v2

Attaches a Network Interface (a Port) to an Instance using the OpenStack Compute (Nova) v2 API.

» Example Usage

» Basic Attachment

» Attachment Specifying a Fixed IP

```
resource "openstack_networking_network_v2" "network_1" {
                = "network 1"
  admin_state_up = "true"
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance 1"
  security_groups = ["default"]
}
resource "openstack_compute_interface_attach_v2" "ai_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
 network_id = "${openstack_networking_port_v2.network_1.id}"
 fixed_ip
           = "10.0.10.10"
}
» Attachment Using an Existing Port
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_port_v2" "port_1" {
                = "port_1"
               = "${openstack_networking_network_v2.network_1.id}"
 network id
 admin_state_up = "true"
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance_1"
  security_groups = ["default"]
}
resource "openstack_compute_interface_attach_v2" "ai_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
 port id
            = "${openstack_networking_port_v2.port_1.id}"
}
```

» Attaching Multiple Interfaces

```
resource "openstack_networking_network_v2" "network_1" {
                 = "network 1"
  admin_state_up = "true"
}
resource "openstack networking port v2" "ports" {
  count
                 = "${format("port-%02d", count.index + 1)}"
 name
               = "${openstack_networking_network_v2.network_1.id}"
 network_id
  admin_state_up = "true"
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance 1"
  security_groups = ["default"]
resource "openstack_compute_interface_attach_v2" "attachments" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
              = "${openstack_networking_port_v2.ports.*.id[count.index]}"
 port_id
Note that the above example will not guarantee that the ports are attached in a
deterministic manner. The ports will be attached in a seemingly random order.
If you want to ensure that the ports are attached in a given order, create explicit
dependencies between the ports, such as:
resource "openstack_networking_network_v2" "network_1" {
                 = "network 1"
  admin_state_up = "true"
}
resource "openstack_networking_port_v2" "ports" {
  count = 2
               = "${format("port-%02d", count.index + 1)}"
 name
 network_id
               = "${openstack networking network v2.network 1.id}"
  admin_state_up = "true"
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance 1"
  security_groups = ["default"]
}
```

```
resource "openstack_compute_interface_attach_v2" "ai_1" {
   instance_id = "${openstack_compute_instance_v2.instance_1.id}"
   port_id = "${openstack_networking_port_v2.ports.*.id[0]}"
}

resource "openstack_compute_interface_attach_v2" "ai_2" {
   instance_id = "${openstack_compute_instance_v2.instance_1.id}"
   port_id = "${openstack_networking_port_v2.ports.*.id[1]}"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to create the interface attachment. If omitted, the region argument of the provider is used. Changing this creates a new attachment.
- instance_id (Required) The ID of the Instance to attach the Port or Network to.
- port_id (Optional) The ID of the Port to attach to an Instance. *NOTE*: This option and network_id are mutually exclusive.
- network_id (Optional) The ID of the Network to attach to an Instance. A port will be created automatically. *NOTE*: This option and port_id are mutually exclusive.
- fixed_ip (Optional) An IP address to assosciate with the port. *NOTE*: This option cannot be used with port_id. You must specify a network_id. The IP address must lie in a range on the supplied network.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- instance_id See Argument Reference above.
- port_id See Argument Reference above.
- network_id See Argument Reference above.
- fixed ip See Argument Reference above.

» Import

Interface Attachments can be imported using the Instance ID and Port ID separated by a slash, e.g.

\$ terraform import openstack_compute_interface_attach_v2.ai_1 89c60255-9bd6-460c-822a-e2b95

» openstack_compute_keypair_v2

Manages a V2 keypair resource within OpenStack.

Important Security Notice The private key generated by this resource will be stored *unencrypted* in your Terraform state file. Use of this resource for production deployments is *not* recommended. Instead, generate a private key file outside of Terraform and distribute it securely to the system where Terraform will be run.

» Example Usage

» Import an Existing Public Key

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new keypair.
- name (Required) A unique name for the keypair. Changing this creates a new keypair.

- public_key (Optional) A pregenerated OpenSSH-formatted public key. Changing this creates a new keypair. If a public key is not specified, then a public/private key pair will be automatically generated. If a pair is created, then destroying this resource means you will lose access to that keypair forever.
- value_specs (Optional) Map of additional options.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- public_key See Argument Reference above.
- fingerprint The fingerprint of the public key.
- private_key The generated private key when no public key is specified.

» Import

Keypairs can be imported using the name, e.g.

\$ terraform import openstack_compute_keypair_v2.my-keypair test-keypair

» openstack_compute_secgroup_v2

Manages a V2 security group resource within OpenStack.

Please note that managing security groups through the OpenStack Compute API has been deprecated. Unless you are using an older OpenStack environment, it is recommended to use the openstack_networking_secgroup_v2 and openstack_networking_secgroup_rule_v2 resources instead, which uses the OpenStack Networking API.

» Example Usage

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a security group. If omitted, the region argument of the provider is used. Changing this creates a new security group.
- name (Required) A unique name for the security group. Changing this updates the name of an existing security group.
- description (Required) A description for the security group. Changing this updates the description of an existing security group.
- rule (Optional) A rule describing how the security group operates. The rule object structure is documented below. Changing this updates the security group rules. As shown in the example above, multiple rule blocks may be used.

The rule block supports:

- from_port (Required) An integer representing the lower bound of the port range to open. Changing this creates a new security group rule.
- to_port (Required) An integer representing the upper bound of the port range to open. Changing this creates a new security group rule.
- ip_protocol (Required) The protocol type that will be allowed. Changing this creates a new security group rule.
- cidr (Optional) Required if from_group_id or self is empty. The IP range that will be the source of network traffic to the security group. Use 0.0.0.0/0 to allow all IP addresses. Changing this creates a new security group rule. Cannot be combined with from_group_id or self.
- from_group_id (Optional) Required if cidr or self is empty. The ID of a group from which to forward traffic to the parent group. Changing

this creates a new security group rule. Cannot be combined with cidr or self.

• self - (Optional) Required if cidr and from_group_id is empty. If true, the security group itself will be added as a source to this ingress rule. Cannot be combined with cidr or from_group_id.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- rule See Argument Reference above.

» Notes

» ICMP Rules

When using ICMP as the ip_protocol, the from_port sets the ICMP type and the to_port sets the ICMP code. To allow all ICMP types, set each value to -1, like so:

```
rule {
  from_port = -1
  to_port = -1
  ip_protocol = "icmp"
  cidr = "0.0.0.0/0"
}
```

A list of ICMP types and codes can be found here.

» Referencing Security Groups

When referencing a security group in a configuration (for example, a configuration creates a new security group and then needs to apply it to an instance being created in the same configuration), it is currently recommended to reference the security group by name and not by ID, like this:

}

» Import

Security Groups can be imported using the id, e.g.

 $\$\ terraform\ import\ openstack_compute_secgroup_v2.my_secgroup\ 1bc30ee9-9d5b-4c30-bdd5-7f1e6632-bdd5-7f1e6652-bdd5-7f1e6652-$

» openstack_compute_servergroup_v2

Manages a V2 Server Group resource within OpenStack.

» Example Usage

```
resource "openstack_compute_servergroup_v2" "test-sg" {
  name = "my-sg"
  policies = ["anti-affinity"]
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. If omitted, the region argument of the provider is used. Changing this creates a new server group.
- name (Required) A unique name for the server group. Changing this creates a new server group.
- policies (Required) The set of policies for the server group. All policies are mutually exclusive. See the Policies section for more information. Changing this creates a new server group.
- value_specs (Optional) Map of additional options.

» Policies

- affinity All instances/servers launched in this group will be hosted on the same compute node.
- anti-affinity All instances/servers launched in this group will be hosted on different compute nodes.

- soft-affinity All instances/servers launched in this group will be hosted on the same compute node if possible, but if not possible they still will be scheduled instead of failure. To use this policy your OpenStack environment should support Compute service API 2.15 or above.
- soft-anti-affinity All instances/servers launched in this group will be hosted on different compute nodes if possible, but if not possible they still will be scheduled instead of failure. To use this policy your OpenStack environment should support Compute service API 2.15 or above.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- policies See Argument Reference above.
- members The instances that are part of this server group.

» Import

Server Groups can be imported using the id, e.g.

\$ terraform import openstack_compute_servergroup_v2.test-sg 1bc30ee9-9d5b-4c30-bdd5-7f1e663:

$ightsymbol{ iny}$ openstack_compute_volume_attach_v2

Attaches a Block Storage Volume to an Instance using the OpenStack Compute (Nova) v2 API.

» Example Usage

» Basic attachment of a single volume to a single instance

```
resource "openstack_compute_volume_attach_v2" "va_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
}
» Attaching multiple volumes to a single instance
resource "openstack_blockstorage_volume_v2" "volumes" {
 name = "${format("vol-%02d", count.index + 1)}"
  size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance 1"
  security_groups = ["default"]
resource "openstack_compute_volume_attach_v2" "attachments" {
            = 2
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volumes.*.id[count.index]}"
}
output "volume devices" {
  value = "${openstack_compute_volume_attach_v2.attachments.*.device}"
Note that the above example will not guarantee that the volumes are attached
in a deterministic manner. The volumes will be attached in a seemingly random
order.
If you want to ensure that the volumes are attached in a given order, create
explicit dependencies between the volumes, such as:
resource "openstack_blockstorage_volume_v2" "volumes" {
  count = 2
 name = "${format("vol-%02d", count.index + 1)}"
  size = 1
}
resource "openstack_compute_instance_v2" "instance_1" {
                  = "instance_1"
  security_groups = ["default"]
```

```
resource "openstack_compute_volume_attach_v2" "attach_1" {
   instance_id = "${openstack_compute_instance_v2.instance_1.id}"
   volume_id = "${openstack_blockstorage_volume_v2.volumes.0.id}"
}

resource "openstack_compute_volume_attach_v2" "attach_2" {
   instance_id = "${openstack_compute_instance_v2.instance_1.id}"
   volume_id = "${openstack_blockstorage_volume_v2.volumes.1.id}"

   depends_on = ["openstack_compute_volume_attach_v2.attach_1"]
}

output "volume devices" {
   value = "${openstack_compute_volume_attach_v2.attachments.*.device}"
}
```

» Using Multiattach-enabled volumes

Multiattach Volumes are dependent upon your OpenStack cloud and not all clouds support multiattach.

```
resource "openstack_blockstorage_volume_v3" "volume_1" {
             = "volume 1"
             = 1
  size
 multiattach = true
}
resource "openstack_compute_instance_v2" "instance_1" {
                 = "instance 1"
  security_groups = ["default"]
}
resource "openstack_compute_instance_v2" "instance_2" {
                 = "instance 2"
  security_groups = ["default"]
}
resource "openstack_compute_volume_attach_v2" "va_1" {
  instance_id = "${openstack_compute_instance_v2.instance_1.id}"
  volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
 multiattach = true
}
resource "openstack_compute_volume_attach_v2" "va_2" {
```

```
instance_id = "${openstack_compute_instance_v2.instance_2.id}"
volume_id = "${openstack_blockstorage_volume_v2.volume_1.id}"
multiattach = true

depends_on = ["openstack_compute_volume_attach_v2.va_1"]
}
```

It is recommended to use depends_on for the attach resources to enforce the volume attachments to happen one at a time.

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. A Compute client is needed to create a volume attachment. If omitted, the region argument of the provider is used. Changing this creates a new volume attachment.
- instance_id (Required) The ID of the Instance to attach the Volume to.
- volume_id (Required) The ID of the Volume to attach to an Instance.
- device (Optional) The device of the volume attachment (ex: /dev/vdc). NOTE: Being able to specify a device is dependent upon the hypervisor in use. There is a chance that the device specified in Terraform will not be the same device the hypervisor chose. If this happens, Terraform will wish to update the device upon subsequent applying which will cause the volume to be detached and reattached indefinitely. Please use with caution.
- multiattach (Optional) Enable attachment of multiattach-capable volumes.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- instance_id See Argument Reference above.
- volume_id See Argument Reference above.
- device See Argument Reference above. *NOTE*: The correctness of this information is dependent upon the hypervisor in use. In some cases, this should not be used as an authoritative piece of information.
- multiattach See Argument Reference above.

» Import

Volume Attachments can be imported using the Instance ID and Volume ID separated by a slash, e.g.

\$ terraform import openstack_compute_volume_attach_v2.va_1 89c60255-9bd6-460c-822a-e2b959ede

» openstack_containerinfra_cluster_v1

Manages a V1 Magnum cluster resource within OpenStack.

» Example Usage

» Create a Cluster

» Argument reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V1 Container Infra client. A Container Infra client is needed to create a cluster. If omitted, the region argument of the provider is used. Changing this creates a new cluster.
- name (Required) The name of the cluster. Changing this updates the name of the existing cluster template.
- project_id (Optional) The project of the cluster. Required if admin wants to create a cluster in another project. Changing this creates a new cluster.
- user_id (Optional) The user of the cluster. Required if admin wants to create a cluster template for another user. Changing this creates a new cluster.
- cluster_template_id (Required) The UUID of the V1 Container Infra cluster template. Changing this creates a new cluster.

- create_timeout (Optional) The timeout (in minutes) for creating the cluster. Changing this creates a new cluster.
- discovery_url (Optional) The URL used for cluster node discovery. Changing this creates a new cluster.
- docker_volume_size (Optional) The size (in GB) of the Docker volume. Changing this creates a new cluster.
- flavor (Optional) The flavor for the nodes of the cluster. Can be set via the OS_MAGNUM_FLAVOR environment variable. Changing this creates a new cluster.
- master_flavor (Optional) The flavor for the master nodes. Can be set via the OS_MAGNUM_MASTER_FLAVOR environment variable. Changing this creates a new cluster.
- keypair (Optional) The name of the Compute service SSH keypair. Changing this creates a new cluster.
- labels (Optional) The list of key value pairs representing additional properties of the cluster. Changing this creates a new cluster.
- master_count (Optional) The number of master nodes for the cluster. Changing this creates a new cluster.
- node_count (Optional) The number of nodes for the cluster. Changing this creates a new cluster.

» Attributes reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- project_id See Argument Reference above.
- created_at The time at which cluster was created.
- updated_at The time at which cluster was created.
- api_address COE API address.
- coe_version COE software version.
- cluster_template_id See Argument Reference above.
- container_version Container software version.
- create_timeout See Argument Reference above.
- discovery_url See Argument Reference above.
- docker_volume_size See Argument Reference above.
- flavor See Argument Reference above.
- master_flavor See Argument Reference above.
- keypair See Argument Reference above.
- labels See Argument Reference above.

- master_count See Argument Reference above.
- node_count See Argument Reference above.
- master_addresses IP addresses of the master node of the cluster.
- node_addresses IP addresses of the node of the cluster.
- stack_id UUID of the Orchestration service stack.

» Import

Clusters can be imported using the id, e.g.

\$ terraform import openstack_containerinfra_cluster_v1.cluster_1 ce0f9463-dd25-474b-9fe8-946

» openstack_containerinfra_clustertemplate_v1

Manages a V1 Magnum cluster template resource within OpenStack.

» Example Usage

» Create a Cluster template

```
resource "openstack_containerinfra_clustertemplate_v1" "clustertemplate_1" {
                        = "clustertemplate_1"
                        = "Fedora-Atomic-27"
  image
                        = "kubernetes"
  coe
                       = "m1.small"
 flavor
                        = "m1.medium"
 master_flavor
 dns_nameserver
                        = "1.1.1.1"
 docker_storage_driver = "devicemapper"
                       = 10
  docker_volume_size
                       = "cinder"
 volume_driver
                       = "flannel"
 network_driver
                       = "vm"
  server_type
 master_lb_enabled
                        = true
  floating_ip_enabled = false
  labels = {
    kube_tag
                                     = "1.11.1"
                                     = "true"
   kube_dashboard_enabled
   prometheus_monitoring
                                     = "true"
   influx_grafana_dashboard_enabled = "true"
}
```

- region (Optional) The region in which to obtain the V1 Container Infra client. A Container Infra client is needed to create a cluster template. If omitted, the region argument of the provider is used. Changing this creates a new cluster template.
- name (Required) The name of the cluster template. Changing this updates the name of the existing cluster template.
- project_id (Optional) The project of the cluster template. Required if admin wants to create a cluster template in another project. Changing this creates a new cluster template.
- user_id (Optional) The user of the cluster template. Required if admin wants to create a cluster template for another user. Changing this creates a new cluster template.
- apiserver_port (Optional) The API server port for the Container Orchestration Engine for this cluster template. Changing this updates the API server port of the existing cluster template.
- coe (Required) The Container Orchestration Engine for this cluster template. Changing this updates the engine of the existing cluster template.
- cluster_distro (Optional) The distro for the cluster (fedora-atomic, coreos, etc.). Changing this updates the cluster distro of the existing cluster template.
- dns_nameserver (Optional) Address of the DNS nameserver that is used in nodes of the cluster. Changing this updates the DNS nameserver of the existing cluster template.
- docker_storage_driver (Optional) Docker storage driver. Changing this updates the Docker storage driver of the existing cluster template.
- docker_volume_size (Optional) The size (in GB) of the Docker volume. Changing this updates the Docker volume size of the existing cluster template.
- external_network_id (Optional) The ID of the external network that will be used for the cluster. Changing this updates the external network ID of the existing cluster template.
- fixed_network (Optional) The fixed network that will be attached to the cluster. Changing this updates the fixed network of the existing cluster template.
- fixed_subnet (Optional) The fixed subnet that will be attached to the cluster. Changing this updates the fixed subnet of the existing cluster

template.

- flavor (Optional) The flavor for the nodes of the cluster. Can be set via the OS_MAGNUM_FLAVOR environment variable. Changing this updates the flavor of the existing cluster template.
- master_flavor (Optional) The flavor for the master nodes. Can be set via the OS_MAGNUM_MASTER_FLAVOR environment variable. Changing this updates the master flavor of the existing cluster template.
- floating_ip_enabled (Optional) Indicates whether created cluster should create floating IP for every node or not. Changing this updates the floating IP enabled attribute of the existing cluster template.
- http_proxy (Optional) The address of a proxy for receiving all HTTP requests and relay them. Changing this updates the HTTP proxy address of the existing cluster template.
- https_proxy (Optional) The address of a proxy for receiving all HTTPS requests and relay them. Changing this updates the HTTPS proxy address of the existing cluster template.
- image (Required) The reference to an image that is used for nodes of the cluster. Can be set via the OS_MAGNUM_IMAGE environment variable. Changing this updates the image attribute of the existing cluster template.
- insecure_registry (Optional) The insecure registry URL for the cluster template. Changing this updates the insecure registry attribute of the existing cluster template.
- keypair_id (Optional) The name of the Compute service SSH keypair. Changing this updates the keypair of the existing cluster template.
- labels (Optional) The list of key value pairs representing additional properties of the cluster template. Changing this updates the labels of the existing cluster template.
- master_lb_enabled (Optional) Indicates whether created cluster should has a loadbalancer for master nodes or not. Changing this updates the attribute of the existing cluster template.
- network_driver (Optional) The name of the driver for the container network. Changing this updates the network driver of the existing cluster template.
- no_proxy (Optional) A comma-separated list of IP addresses that shouldn't be used in the cluster. Changing this updates the no proxy list of the existing cluster template.
- public (Optional) Indicates whether cluster template should be public. Changing this updates the public attribute of the existing cluster template.

- registry_enabled (Optional) Indicates whether Docker registry is enabled in the cluster. Changing this updates the registry enabled attribute of the existing cluster template.
- server_type (Optional) The server type for the cluster template. Changing this updates the server type of the existing cluster template.
- tls_disabled (Optional) Indicates whether the TLS should be disabled in the cluster. Changing this updates the attribute of the existing cluster.
- volume_driver (Optional) The name of the driver that is used for the volumes of the cluster nodes. Changing this updates the volume driver of the existing cluster template.

» Attributes reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- project_id See Argument Reference above.
- created_at The time at which cluster template was created.
- updated_at The time at which cluster template was created.
- apiserver_port See Argument Reference above.
- coe See Argument Reference above.
- cluster_distro See Argument Reference above.
- dns_nameserver See Argument Reference above.
- docker_storage_driver See Argument Reference above.
- $docker_volume_size$ See Argument Reference above.
- external_network_id See Argument Reference above.
- fixed_network See Argument Reference above.
- fixed subnet See Argument Reference above.
- flavor See Argument Reference above.
- master_flavor See Argument Reference above.
- floating_ip_enabled See Argument Reference above.
- http_proxy See Argument Reference above.
- https_proxy See Argument Reference above.
- image See Argument Reference above.
- insecure_registry See Argument Reference above.
- keypair_id See Argument Reference above.
- labels See Argument Reference above.
- links A list containing associated cluster template links.
- master 1b enabled See Argument Reference above.
- network_driver See Argument Reference above.
- no_proxy See Argument Reference above.
- public See Argument Reference above.
- registry_enabled See Argument Reference above.

- server_type See Argument Reference above.
- tls_disabled See Argument Reference above.
- volume_driver See Argument Reference above.

» Import

Cluster templates can be imported using the id, e.g.

\$ terraform import openstack_containerinfra_clustertemplate_v1.clustertemplate_1 b9a45c5c-cc

» openstack_db_instance_v1

Manages a V1 DB instance resource within OpenStack.

» Example Usage

» Instance

```
resource "openstack_db_instance_v1" "test" {
    region = "region-test"
    name = "test"
    flavor_id = "31792d21-c355-4587-9290-56c1ed0ca376"
    size = 8

    network {
        uuid = "c0612505-caf2-4fb0-b7cb-56a0240a2b12"
    }

    datastore {
        version = "mysql-5.7"
        type = "mysql"
    }
}
```

» Argument Reference

- region (Required) The region in which to create the db instance. Changing this creates a new instance.
- name (Required) A unique name for the resource.

- flavor_id (Required) The flavor ID of the desired flavor for the instance. Changing this creates new instance.
- configuration_id (Optional) Configuration ID to be attached to the instance. Database instance will be rebooted when configuration is detached.
- size (Required) Specifies the volume size in GB. Changing this creates new instance.
- datastore (Required) An array of database engine type and version.
 The datastore object structure is documented below. Changing this creates a new instance.
- network (Optional) An array of one or more networks to attach to the instance. The network object structure is documented below. Changing this creates a new instance.
- user (Optional) An array of username, password, host and databases. The user object structure is documented below.
- database (Optional) An array of database name, charset and collate.

 The database object structure is documented below.

The datastore block supports:

- type (Required) Database engine type to be used in new instance. Changing this creates a new instance.
- version (Required) Version of database engine type to be used in new instance. Changing this creates a new instance.

The network block supports:

- uuid (Required unless port is provided) The network UUID to attach to the instance. Changing this creates a new instance.
- port (Required unless uuid is provided) The port UUID of a network to attach to the instance. Changing this creates a new instance.
- fixed_ip_v4 (Optional) Specifies a fixed IPv4 address to be used on this network. Changing this creates a new instance.
- fixed_ip_v6 (Optional) Specifies a fixed IPv6 address to be used on this network. Changing this creates a new instance.

The user block supports:

- name (Optional) Username to be created on new instance. Changing this
 creates a new instance.
- password (Optional) User's password. Changing this creates a new instance.

- host (Optional) An ip address or % sign indicating what ip addresses can connect with this user credentials. Changing this creates a new instance.
- databases (Optional) A list of databases that user will have access to. If not specified, user has access to all databases on the instance. Changing this creates a new instance.

The database block supports:

- name (Optional) Database to be created on new instance. Changing this
 creates a new instance.
- collate (Optional) Database collation. Changing this creates a new instance.
- charset (Optional) Database character set. Changing this creates a new instance.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- size See Argument Reference above.
- flavor_id See Argument Reference above.
- configuration_id See Argument Reference above.
- datastore/type See Argument Reference above.
- datastore/version See Argument Reference above.
- network/uuid See Argument Reference above.
- network/port See Argument Reference above.
- network/fixed_ip_v4 The Fixed IPv4 address of the Instance on that network.
- network/fixed_ip_v6 The Fixed IPv6 address of the Instance on that
- database/name See Argument Reference above.
- database/collate See Argument Reference above.
- database/charset See Argument Reference above.
- user/name See Argument Reference above.
- user/password See Argument Reference above.
- user/databases See Argument Reference above.
- user/host See Argument Reference above.

» openstack_db_database_v1

Manages a V1 DB database resource within OpenStack.

» Example Usage

» Database

» Argument Reference

The following arguments are supported:

- name (Required) A unique name for the resource.
- instance_id (Required) The ID for the database instance.

» Attributes Reference

The following attributes are exported:

- region Openstack region resource is created in.
- name See Argument Reference above.
- instance_id See Argument Reference above.

» Import

Databases can be imported by using instance-id/db-name, e.g.

\$ terraform import openstack_db_database_v1.mydb 7b9e3cd3-00d9-449c-b074-8439f8e274fa/mydb

$\ \ \, \text{openstack_db_user_v1}$

Manages a V1 DB user resource within OpenStack.

» Example Usage

» User

```
password = "password"
  databases = ["testdb"]
}
```

The following arguments are supported:

- name (Required) A unique name for the resource.
- instance (Required) The ID for the database instance.
- password (Required) User's password.
- databases (Optional) A list of database user should have access to.

» Attributes Reference

The following attributes are exported:

- region Openstack region resource is created in.
- name See Argument Reference above.
- instance See Argument Reference above.
- password See Argument Reference above.
- databases See Argument Reference above.

ightarrow openstack_db_configuration_v1

Manages a V1 DB configuration resource within OpenStack.

» Example Usage

» Configuration

```
name = "max_connections"
value = 200
}
```

The following arguments are supported:

- region (Required) The region in which to create the db instance. Changing this creates a new instance.
- name (Required) A unique name for the resource.
- description (Optional) Description of the resource.
- datastore (Required) An array of database engine type and version.
 The datastore object structure is documented below. Changing this creates resource.
- configuration (Optional) An array of configuration parameter name and value. Can be specified multiple times. The configuration object structure is documented below.

The datastore block supports:

- type (Required) Database engine type to be used with this configuration. Changing this creates a new resource.
- version (Required) Version of database engine type to be used with this configuration. Changing this creates a new resource.

The configuration block supports:

- name (Optional) Configuration parameter name. Changing this creates a new resource.
- value (Optional) Configuration parameter value. Changing this creates a new resource.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- datastore/type See Argument Reference above.
- datastore/version See Argument Reference above.
- configuration/name See Argument Reference above.
- configuration/value See Argument Reference above.

» openstack_dns_recordset_v2

Manages a DNS record set in the OpenStack DNS Service.

» Example Usage

» Automatically detect the correct network

```
resource "openstack_dns_zone_v2" "example_zone" {
   name = "example.com."
   email = "email2@example.com"
   description = "a zone"
   ttl = 6000
   type = "PRIMARY"
}

resource "openstack_dns_recordset_v2" "rs_example_com" {
   zone_id = "${openstack_dns_zone_v2.example_zone.id}"
   name = "rs.example.com."
   description = "An example record set"
   ttl = 3000
   type = "A"
   records = ["10.0.0.1"]
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 DNS client. If omitted, the region argument of the provider is used. Changing this creates a new DNS record set.
- zone_id (Required) The ID of the zone in which to create the record set. Changing this creates a new DNS record set.
- name (Required) The name of the record set. Note the . at the end of the name. Changing this creates a new DNS record set.
- type (Optional) The type of record set. Examples: "A", "MX". Changing this creates a new DNS record set.
- ttl (Optional) The time to live (TTL) of the record set.
- description (Optional) A description of the record set.

- records (Optional) An array of DNS records. *Note:* if an IPv6 address contains brackets ([]), the brackets will be stripped and the modified address will be recorded in the state.
- value_specs (Optional) Map of additional options. Changing this creates a new record set.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- type See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- records See Argument Reference above.
- zone_id See Argument Reference above.
- value_specs See Argument Reference above.

» Import

This resource can be imported by specifying the zone ID and recordset ID, separated by a forward slash.

\$ terraform import openstack_dns_recordset_v2.recordset_1 <zone_id>/<recordset_id>

» openstack_dns_zone_v2

Manages a DNS zone in the OpenStack DNS Service.

» Example Usage

» Automatically detect the correct network

```
resource "openstack_dns_zone_v2" "example.com" {
  name = "example.com."
  email = "jdoe@example.com"
  description = "An example zone"
  ttl = 3000
  type = "PRIMARY"
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Compute client. Keypairs are associated with accounts, but a Compute client is needed to create one. If omitted, the region argument of the provider is used. Changing this creates a new DNS zone.
- name (Required) The name of the zone. Note the . at the end of the name. Changing this creates a new DNS zone.
- email (Optional) The email contact for the zone record.
- type (Optional) The type of zone. Can either be PRIMARY or SECONDARY. Changing this creates a new zone.
- attributes (Optional) Attributes for the DNS Service scheduler. Changing this creates a new zone.
- ttl (Optional) The time to live (TTL) of the zone.
- description (Optional) A description of the zone.
- masters (Optional) An array of master DNS servers. For when type is SECONDARY.
- value_specs (Optional) Map of additional options. Changing this creates a new zone.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- email See Argument Reference above.
- type See Argument Reference above.
- attributes See Argument Reference above.
- ttl See Argument Reference above.
- description See Argument Reference above.
- masters See Argument Reference above.
- value_specs See Argument Reference above.

» Import

This resource can be imported by specifying the zone ID:

\$ terraform import openstack_dns_zone_v2.zone_1 <zone_id>

» openstack_identity_project_v3

Manages a V3 Project resource within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

» Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
  name = "project_1"
  description = "A project"
}
```

» Argument Reference

The following arguments are supported:

- description (Optional) A description of the project.
- domain_id (Optional) The domain this project belongs to.
- enabled (Optional) Whether the project is enabled or disabled. Valid values are true and false.
- is_domain (Optional) Whether this project is a domain. Valid values are true and false.
- name (Optional) The name of the project.
- parent_id (Optional) The parent of this project.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new User.

» Attributes Reference

The following attributes are exported:

- domain_id See Argument Reference above.
- parent_id See Argument Reference above.

» Import

Projects can be imported using the id, e.g.

\$ terraform import openstack_identity_project_v3.project_1 89c60255-9bd6-460c-822a-e2b959ede

» openstack_identity_role_v3

Manages a V3 Role resource within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

» Example Usage

```
resource "openstack_identity_role_v3" "role_1" {
  name = "role_1"
}
```

» Argument Reference

The following arguments are supported:

- name The name of the role.
- domain_id (Optional) The domain the role belongs to.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new Role.

» Attributes Reference

The following attributes are exported:

- name See Argument Reference above.
- domain_id See Argument Reference above.
- region See Argument Reference above.

» Import

Roles can be imported using the id, e.g.

\$ terraform import openstack_identity_role_v3.role_1 89c60255-9bd6-460c-822a-e2b959ede9d2

» openstack_identity_role_assignment_v3

Manages a V3 Role assignment within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

» Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = "project_1"
}

resource "openstack_identity_user_v3" "user_1" {
   name = "user_1"
   default_project_id = "${openstack_identity_project_v3.project_1.id}"
}

resource "openstack_identity_role_v3" "role_1" {
   name = "role_1"
}

resource "openstack_identity_role_assignment_v3" "role_assignment_1" {
   user_id = "${openstack_identity_user_v3.user_1.id}"
   project_id = "${openstack_identity_project_v3.project_1.id}"
   role_id = "${openstack_identity_role_v3.role_1.id}"
}
```

» Argument Reference

- domain_id (Optional; Required if project_id is empty) The domain to assign the role in.
- group_id (Optional; Required if user_id is empty) The group to assign the role to.
- project_id (Optional; Required if domain_id is empty) The project to assign the role in.
- user_id (Optional; Required if group_id is empty) The user to assign
 the role to.
- role_id (Required) The role to assign.

» Attributes Reference

The following attributes are exported:

- domain_id See Argument Reference above.
- project_id See Argument Reference above.
- group_id See Argument Reference above.
- user_id See Argument Reference above.
- role_id See Argument Reference above.

» openstack_identity_user_v3

Manages a V3 User resource within OpenStack Keystone.

Note: You must have admin privileges in your OpenStack cloud to use this resource.

» Example Usage

```
resource "openstack_identity_project_v3" "project_1" {
   name = "project_1"
}

resource "openstack_identity_user_v3" "user_1" {
   default_project_id = "${openstack_identity_project_v3.project_1.id}}"
   name = "user_1"
   description = "A user"

password = "password123"

ignore_change_password_upon_first_use = true

multi_factor_auth_enabled = true

multi_factor_auth_rule {
   rule = ["password", "totp"]
}

multi_factor_auth_rule {
   rule = ["password"]
}

extra {
   email = "user_1@foobar.com"
```

```
}
}
```

The following arguments are supported:

- description (Optional) A description of the user.
- default_project_id (Optional) The default project this user belongs to.
- domain_id (Optional) The domain this user belongs to.
- enabled (Optional) Whether the user is enabled or disabled. Valid values are true and false.
- extra (Optional) Free-form key/value pairs of extra information.
- ignore_change_password_upon_first_use (Optional) User will not
 have to change their password upon first use. Valid values are true and
 false.
- ignore_password_expiry (Optional) User's password will not expire. Valid values are true and false.
- ignore_lockout_failure_attempts (Optional) User will not have a failure lockout placed on their account. Valid values are true and false.
- multi_factor_auth_enabled (Optional) Whether to enable multi-factor authentication. Valid values are true and false.
- multi_factor_auth_rule (Optional) A multi-factor authentication rule. The structure is documented below. Please see the Ocata release notes for more information on how to use multi-factor rules.
- name (Optional) The name of the user.
- password (Optional) The password for the user.
- region (Optional) The region in which to obtain the V3 Keystone client. If omitted, the region argument of the provider is used. Changing this creates a new User.

The multi_factor_auth_rule block supports:

• rule - (Required) A list of authentication plugins that the user must authenticate with.

» Attributes Reference

The following attributes are exported:

• domain_id - See Argument Reference above.

» Import

Users can be imported using the id, e.g.

 $\$\ terraform\ import\ openstack_identity_user_v3.user_1\ 89c60255-9bd6-460c-822a-e2b959ede9d2$

» openstack_images_image_v2

Manages a V2 Image resource within OpenStack Glance.

» Example Usage

```
resource "openstack_images_image_v2" "rancheros" {
  name = "RancherOS"
  image_source_url = "https://releases.rancher.com/os/latest/rancheros-openstack.img"
  container_format = "bare"
  disk_format = "qcow2"

  properties = {
    key = "value"
  }
}
```

» Argument Reference

- container_format (Required) The container format. Must be one of "ami", "ari", "aki", "bare", "ovf".
- disk_format (Required) The disk format. Must be one of "ami", "ari", "aki", "vhd", "vmdk", "raw", "qcow2", "vdi", "iso".
- local_file_path (Optional) This is the filepath of the raw image file that will be uploaded to Glance. Conflicts with image_source_url.

- image_cache_path (Optional) This is the directory where the images will be downloaded. Images will be stored with a filename corresponding to the url's md5 hash. Defaults to "\$HOME/.terraform/image_cache"
- image_source_url (Optional) This is the url of the raw image that will be downloaded in the image_cache_path before being uploaded to Glance. Glance is able to download image from internet but the gophercloud library does not yet provide a way to do so. Conflicts with local file path.
- min_disk_gb (Optional) Amount of disk space (in GB) required to boot image. Defaults to 0.
- min_ram_mb (Optional) Amount of ram (in MB) required to boot image.
 Defauts to 0.
- name (Required) The name of the image.
- properties (Optional) A map of key/value pairs to set freeform information about an image. See the "Notes" section for further information about properties.
- protected (Optional) If true, image will not be deletable. Defaults to false.
- region (Optional) The region in which to obtain the V2 Glance client. A Glance client is needed to create an Image that can be used with a compute instance. If omitted, the region argument of the provider is used. Changing this creates a new Image.
- tags (Optional) The tags of the image. It must be a list of strings. At this time, it is not possible to delete all tags of an image.
- verify_checksum (Optional) If false, the checksum will not be verified once the image is finished uploading. Defaults to true.
- visibility (Optional) The visibility of the image. Must be one of "public", "private", "community", or "shared". The ability to set the visibility depends upon the configuration of the OpenStack cloud.

» Attributes Reference

The following attributes are exported:

- checksum The checksum of the data associated with the image.
- container_format See Argument Reference above.
- created_at The date the image was created.
- disk_format See Argument Reference above.
- file the trailing path after the glance endpoint that represent the location of the image or the path to retrieve it.

- id A unique ID assigned by Glance.
- metadata The metadata associated with the image. Image metadata allow for meaningfully define the image properties and tags. See https://docs.openstack.org/glance/latest/user/metadefs-concepts.html.
- min_disk_gb See Argument Reference above.
- min_ram_mb See Argument Reference above.
- name See Argument Reference above.
- owner The id of the openstack user who owns the image.
- properties See Argument Reference above.
- protected See Argument Reference above.
- region See Argument Reference above.
- schema The path to the JSON-schema that represent the image or image
- size_bytes The size in bytes of the data associated with the image.
- status The status of the image. It can be "queued", "active" or "saving".
- tags See Argument Reference above.
- updated_at The date the image was last updated.
- update_at (Deprecated use updated_at instead)
- visibility See Argument Reference above.

» Notes

» Properties

This resource supports the ability to add properties to a resource during creation as well as add, update, and delete properties during an update of this resource.

Newer versions of OpenStack are adding some read-only properties to each image. These properties start with the prefix os_. If these properties are detected, this resource will automatically reconcile these with the user-provided properties.

In addition, the direct_url property is also automatically reconciled if the Image Service set it.

» Import

Images can be imported using the id, e.g.

\$ terraform import openstack_images_image_v2.rancheros 89c60255-9bd6-460c-822a-e2b959ede9d2

${\tt "openstack_networking_addressscope_v2}$

Manages a V2 Neutron addressscope resource within OpenStack.

» Example Usage

» Create an Address-scope

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron address-scope. If omitted, the region argument of the provider is used. Changing this creates a new address-scope.
- name (Required) The name of the address-scope. Changing this updates the name of the existing address-scope.
- ip_version (Optional) IP version, either 4 (default) or 6. Changing this creates a new address-scope.
- shared (Optional) Indicates whether this address-scope is shared across all projects. Changing this updates the shared status of the existing address-scope.
- project_id (Optional) The owner of the address-scope. Required if admin wants to create a address-scope for another project. Changing this creates a new address-scope.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- ip_version See Argument Reference above.
- shared See Argument Reference above.
- project_id See Argument Reference above.

» Import

Address-scopes can be imported using the id, e.g.

\$ terraform import openstack_networking_addressscope_v2.addressscope_1 9cc35860-522a-4d35-9

» openstack_networking_floatingip_v2

Manages a V2 floating IP resource within OpenStack Neutron (networking) that can be used for load balancers. These are similar to Nova (compute) floating IP resources, but only compute floating IPs can be used with compute instances.

» Example Usage

```
resource "openstack_networking_floatingip_v2" "floatip_1" {
  pool = "public"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a floating IP that can be used with another networking resource, such as a load balancer. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- description (Optional) Human-readable description for the floating IP.
- pool (Required) The name of the pool from which to obtain the floating IP. Changing this creates a new floating IP.

- port_id (Optional) ID of an existing port with at least one IP address to associate with this floating IP.
- tenant_id (Optional) The target tenant ID in which to allocate the floating IP, if you specify this together with a port_id, make sure the target port belongs to the same tenant. Changing this creates a new floating IP (which may or may not have a different address)
- address (Optional) The actual/specific floating IP to obtain. By default, non-admin users are not able to specify a floating IP, so you must either be an admin user or have had a custom policy or role applied to your OpenStack user or project.
- fixed_ip Fixed IP of the port to associate with this floating IP. Required if the port has multiple fixed IPs.
- subnet_id (Optional) The subnet ID of the floating IP pool. Specify this if the floating IP network has multiple subnets.
- value_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the floating IP.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- description See Argument Reference above.
- pool See Argument Reference above.
- address The actual floating IP address itself.
- port_id ID of associated port.
- tenant id the ID of the tenant in which to create the floating IP.
- fixed_ip The fixed IP which the floating IP maps to.
- tags See Argument Reference above.
- all_tags The collection of tags assigned on the floating IP, which have been explicitly and implicitly added.

» Import

Floating IPs can be imported using the id, e.g.

\$ terraform import openstack networking floatingip v2.floatip 1 2c7f39f3-702b-48d1-940c-b503

» openstack_networking_floatingip_associate_v2

Associates a floating IP to a port. This is useful for situations where you have a pre-allocated floating IP or are unable to use the openstack_networking_floatingip_v2 resource to create a floating IP.

» Example Usage

```
resource "openstack_networking_port_v2" "port_1" {
   network_id = "a5bbd213-e1d3-49b6-aed1-9df60ea94b9a"
}
resource "openstack_networking_floatingip_associate_v2" "fip_1" {
   floating_ip = "1.2.3.4"
   port_id = "${openstack_networking_port_v2.port_1.id}"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a floating IP that can be used with another networking resource, such as a load balancer. If omitted, the region argument of the provider is used. Changing this creates a new floating IP (which may or may not have a different address).
- floating_ip (Required) IP Address of an existing floating IP.
- port_id (Required) ID of an existing port with at least one IP address to associate with this floating IP.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- floating_ip See Argument Reference above.
- port_id See Argument Reference above.

» Import

Floating IP associations can be imported using the id of the floating IP, e.g.

» openstack_networking_network_v2

Manages a V2 Neutron network resource within OpenStack.

» Example Usage

```
resource "openstack_networking_network_v2" "network_1" {
                = "network_1"
 admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
           = "subnet_1"
 network_id = "${openstack_networking_network_v2.network_1.id}"
         = "192.168.199.0/24"
 ip_version = 4
resource "openstack_compute_secgroup_v2" "secgroup_1" {
            = "secgroup_1"
 description = "a security group"
 rule {
   from_port = 22
   to_port = 22
   ip_protocol = "tcp"
              = "0.0.0.0/0"
   cidr
 }
}
resource "openstack_networking_port_v2" "port_1" {
                    = "port_1"
 name
 network id
                   = "${openstack_networking_network_v2.network_1.id}"
                  = "true"
 admin_state_up
 security_group_ids = ["${openstack_compute_secgroup_v2.secgroup_1.id}"]
 fixed_ip {
    "subnet_id" = "${openstack_networking_subnet_v2.subnet_1.id}"
    "ip_address" = "192.168.199.10"
 }
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron network. If omitted, the region argument of the provider is used. Changing this creates a new network.
- name (Optional) The name of the network. Changing this updates the name of the existing network.
- description (Optional) Human-readable description of the network. Changing this updates the name of the existing network.
- shared (Optional) Specifies whether the network resource can be accessed by any tenant or not. Changing this updates the sharing capabilities of the existing network.
- external (Optional) Specifies whether the network resource has the external routing facility. Valid values are true and false. Defaults to false. Changing this updates the external attribute of the existing network.
- tenant_id (Optional) The owner of the network. Required if admin wants to create a network for another tenant. Changing this creates a new network.
- admin_state_up (Optional) The administrative state of the network. Acceptable values are "true" and "false". Changing this value updates the state of the existing network.
- segments (Optional) An array of one or more provider segment objects.
- value_specs (Optional) Map of additional options.
- availability_zone_hints (Optional) An availability zone is used to make network resources highly available. Used for resources with high availability so that they are scheduled on different availability zones. Changing this creates a new network.

- tags (Optional) A set of string tags for the network.
- transparent_vlan (Optional) Specifies whether the network resource has the VLAN transparent attribute set. Valid values are true and false. Defaults to false. Changing this updates the transparent_vlan attribute of the existing network.

The segments block supports:

- physical_network The physical network where this network is implemented.
- segmentation_id An isolated segment on the physical network.
- network_type The type of physical network.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- shared See Argument Reference above.
- external See Argument Reference above.
- tenant_id See Argument Reference above.
- admin_state_up See Argument Reference above.
- availability_zone_hints See Argument Reference above.
- tags See Argument Reference above.
- all_tags The collection of tags assigned on the network, which have been explicitly and implicitly added.
- transparent_vlan See Argument Reference above.

» Import

Networks can be imported using the id, e.g.

\$ terraform import openstack_networking_network_v2.network_1 d90ce693-5ccf-4136-a0ed-152ce4

» openstack_networking_port_v2

Manages a V2 port resource within OpenStack.

» Example Usage

resource "openstack_networking_network_v2" "network_1" {

```
name = "network_1"
admin_state_up = "true"
}

resource "openstack_networking_port_v2" "port_1" {
   name = "port_1"
   network_id = "${openstack_networking_network_v2.network_1.id}"
   admin_state_up = "true"
}
```

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new port.
- name (Optional) A unique name for the port. Changing this updates the name of an existing port.
- description (Optional) Human-readable description of the floating IP. Changing this updates the description of an existing port.
- network_id (Required) The ID of the network to attach the port to. Changing this creates a new port.
- admin_state_up (Optional) Administrative up/down status for the port (must be "true" or "false" if provided). Changing this updates the admin_state_up of an existing port.
- mac_address (Optional) Specify a specific MAC address for the port. Changing this creates a new port.
- tenant_id (Optional) The owner of the Port. Required if admin wants to create a port for another tenant. Changing this creates a new port.
- device_owner (Optional) The device owner of the Port. Changing this creates a new port.
- security_group_ids (Optional Conflicts with no_security_groups) A list of security group IDs to apply to the port. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).
- no_security_groups (Optional Conflicts with security_group_ids)
 If set to true, then no security groups are applied to the port. If set to
 false and no security_group_ids are specified, then the Port will yield

- to the default behavior of the Networking service, which is to usually apply the "default" security group.
- device_id (Optional) The ID of the device attached to the port. Changing this creates a new port.
- fixed_ip (Optional Conflicts with no_fixed_ip) An array of desired IPs for this port. The structure is described below.
- no_fixed_ip (Optional Conflicts with fixed_ip) Create a port with
 no fixed IP address. This will also remove any fixed IPs previously set on
 a port. true is the only valid value for this argument.
- allowed_address_pairs (Optional) An IP/MAC Address pair of additional IP addresses that can be active on this port. The structure is described below.
- extra_dhcp_option (Optional) An extra DHCP option that needs to be configured on the port. The structure is described below. Can be specified multiple times.
- value_specs (Optional) Map of additional options.

The fixed_ip block supports:

- subnet_id (Required) Subnet in which to allocate IP address for this port.
- ip_address (Optional) IP address desired in the subnet for this port. If you don't specify ip_address, an available IP address from the specified subnet will be allocated to this port. This field will not be populated if it is left blank or omitted. To retrieve the assigned IP address, use the all_fixed_ips attribute.

The allowed_address_pairs block supports:

- ip address (Required) The additional IP address.
- mac address (Optional) The additional MAC address.
- tags (Optional) A set of string tags for the port.

The extra_dhcp_option block supports:

- name (Required) Name of the DHCP option.
- value (Required) Value of the DHCP option.
- ip_version (Optional) IP protocol version. Defaults to 4.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- description See Argument Reference above.
- admin_state_up See Argument Reference above.
- mac_address See Argument Reference above.
- tenant_id See Argument Reference above.
- device_owner See Argument Reference above.
- security_group_ids See Argument Reference above.
- device_id See Argument Reference above.
- fixed_ip See Argument Reference above.
- all_fixed_ips The collection of Fixed IP addresses on the port in the order returned by the Network v2 API.
- all_security_group_ids The collection of Security Group IDs on the port which have been explicitly and implicitly added.
- extra dhcp option See Argument Reference above.
- tags See Argument Reference above.
- all_tags The collection of tags assigned on the port, which have been explicitly and implicitly added.

» Import

Ports can be imported using the id, e.g.

\$ terraform import openstack_networking_port_v2.port_1 eae26a3e-1c33-4cc1-9c31-0cd729c438a1

» Notes

» Ports and Instances

There are some notes to consider when connecting Instances to networks using Ports. Please see the openstack_compute_instance_v2 documentation for further documentation.

$ightsymbol{"}$ openstack_networking_port_secgroup_associate_v2

Manages a V2 port's security groups within OpenStack. Useful, when the port was created not by Terraform (e.g. Manila or LBaaS). It should not be used, when the port was created directly within Terraform.

When the resource is deleted, Terraform doesn't delete the port, but unsets the list of user defined security group IDs. However, if enforce is set to true and the resource is deleted, Terraform will remove all assigned security group IDs.

» Example Usage

» Append a security group to an existing port data "openstack_networking_port_v2" "system_port" { $fixed_ip = "10.0.0.10"$ } data "openstack_networking_secgroup_v2" "secgroup" { name = "secgroup" } resource "openstack_networking_port_secgroup_associate_v2" "port_1" { port_id = "\${data.openstack_networking_port_v2.system_port.id}" security_group_ids = ["\${data.openstack_networking_secgroup_v2.secgroup.id}",] } » Enforce a security group to an existing port data "openstack_networking_port_v2" "system_port" { $fixed_ip = "10.0.0.10"$ } data "openstack_networking_secgroup_v2" "secgroup" { name = "secgroup" } resource "openstack_networking_port_secgroup_associate_v2" "port_1" { port_id = "\${data.openstack_networking_port_v2.system_port.id}" enforce = "true" security_group_ids = ["\${data.openstack_networking_secgroup_v2.secgroup.id}", ٦ } » Remove all security groups from an existing port data "openstack_networking_port_v2" "system_port" { $fixed_ip = "10.0.0.10"$ } resource "openstack_networking_port_secgroup_associate_v2" "port_1" {

```
port_id = "${data.openstack_networking_port_v2.system_port.id}"
enforce = "true"
security_group_ids = []
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to manage a port. If omitted, the region argument of the provider is used. Changing this creates a new resource.
- port_id (Required) An UUID of the port to apply security groups to.
- security_group_ids (Required) A list of security group IDs to apply to the port. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).
- enforce (Optional) Whether to replace or append the list of security groups, specified in the security_group_ids. Defaults to false.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- port_id See Argument Reference above.
- security_group_ids See Argument Reference above.
- all_security_group_ids The collection of Security Group IDs on the port which have been explicitly and implicitly added.

» openstack_networking_router_interface_v2

Manages a V2 router interface resource within OpenStack.

» Example Usage

```
resource "openstack_networking_subnet_v2" "subnet_1" {
   network_id = "${openstack_networking_network_v2.network_1.id}"
   cidr = "192.168.199.0/24"
   ip_version = 4
}

resource "openstack_networking_router_v2" "router_1" {
   name = "my_router"
   external_network_id = "f67f0d72-0ddf-11e4-9d95-e1f29f417e2f"
}

resource "openstack_networking_router_interface_v2" "router_interface_1" {
   router_id = "${openstack_networking_router_v2.router_1.id}"
   subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a router. If omitted, the region argument of the provider is used. Changing this creates a new router interface.
- router_id (Required) ID of the router this interface belongs to. Changing this creates a new router interface.
- subnet_id ID of the subnet this interface connects to. Changing this creates a new router interface.
- port_id ID of the port this interface connects to. Changing this creates a new router interface.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- router_id See Argument Reference above.
- subnet_id See Argument Reference above.
- port_id See Argument Reference above.

» Import

Router Interfaces can be imported using the port id, e.g.

```
$ openstack port list --router <router name or id>
$ terraform import openstack_networking_router_interface_v2.int_1 <port id from above output</pre>
```

» openstack_networking_router_route_v2

Creates a routing entry on a OpenStack V2 router.

» Example Usage

```
resource "openstack_networking_router_v2" "router_1" {
                = "router_1"
 admin_state_up = "true"
}
resource "openstack_networking_network_v2" "network_1" {
               = "network 1"
 admin_state_up = "true"
resource "openstack_networking_subnet_v2" "subnet_1" {
 network_id = "${openstack_networking_network_v2.network_1.id}"
            = "192.168.199.0/24"
  ip_version = 4
resource "openstack_networking_router_interface_v2" "int_1" {
 router_id = "${openstack_networking_router_v2.router_1.id}"
 subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_networking_router_route_v2" "router_route_1" {
 depends_on
               = ["openstack_networking_router_interface_v2.int_1"]
              = "${openstack_networking_router_v2.router_1.id}"
 router_id
 destination_cidr = "10.0.1.0/24"
             = "192.168.199.254"
 next hop
}
```

» Argument Reference

The following arguments are supported:

• region - (Optional) The region in which to obtain the V2 networking client. A networking client is needed to configure a routing entry on a

router. If omitted, the **region** argument of the provider is used. Changing this creates a new routing entry.

- router_id (Required) ID of the router this routing entry belongs to. Changing this creates a new routing entry.
- destination_cidr (Required) CIDR block to match on the packet's destination IP. Changing this creates a new routing entry.
- next_hop (Required) IP address of the next hop gateway. Changing this
 creates a new routing entry.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- router_id See Argument Reference above.
- destination_cidr See Argument Reference above.
- next_hop See Argument Reference above.

» Notes

The next_hop IP address must be directly reachable from the router at the openstack_networking_router_route_v2 resource creation time. You can ensure that by explicitly specifying a dependency on the openstack_networking_router_interface_v2 resource that connects the next hop to the router, as in the example above.

» Import

```
Routing entries can be imported using a combined ID using the following format: <router_id>-route-<destination_cidr>-<next_hop>
```

\$ terraform import openstack_networking_router_route_v2.router_route_1 686fe248-386c-4f70-9

» openstack_networking_router_v2

Manages a V2 router resource within OpenStack.

» Example Usage

```
admin_state_up = true
external_network_id = "f67f0d72-0ddf-11e4-9d95-e1f29f417e2f"
}
```

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a router. If omitted, the region argument of the provider is used. Changing this creates a new router.
- name (Optional) A unique name for the router. Changing this updates the name of an existing router.
- description (Optional) Human-readable description for the router.
- admin_state_up (Optional) Administrative up/down status for the router (must be "true" or "false" if provided). Changing this updates the admin_state_up of an existing router.
- distributed (Optional) Indicates whether or not to create a distributed router. The default policy setting in Neutron restricts usage of this property to administrative users only.
- external_gateway (Deprecated use external_network_id instead)
 The network UUID of an external gateway for the router. A router with
 an external gateway is required if any compute instances or load balancers
 will be using floating IPs. Changing this updates the external gateway of
 an existing router.
- external_network_id (Optional) The network UUID of an external gateway for the router. A router with an external gateway is required if any compute instances or load balancers will be using floating IPs. Changing this updates the external gateway of the router.
- enable_snat (Optional) Enable Source NAT for the router. Valid values are "true" or "false". An external_network_id has to be set in order to set this property. Changing this updates the enable_snat of the router.
- external_fixed_ip (Optional) An external fixed IP for the router. This can be repeated. The structure is described below. An external_network_id has to be set in order to set this property. Changing this updates the external fixed IPs of the router.
- tenant_id (Optional) The owner of the floating IP. Required if admin wants to create a router for another tenant. Changing this creates a new router.

- value_specs (Optional) Map of additional driver-specific options.
- tags (Optional) A set of string tags for the router.
- vendor_options (Optional) Map of additional vendor-specific options. Supported options are described below.
- availability_zone_hints (Optional) An availability zone is used to make network resources highly available. Used for resources with high availability so that they are scheduled on different availability zones. Changing this creates a new router.

The external_fixed_ip block supports:

- subnet_id (Optional) Subnet in which the fixed IP belongs to.
- ip address (Optional) The IP address to set on the router.

The vendor_options block supports:

set_router_gateway_after_create - (Optional) Boolean to control
whether the Router gateway is assigned during creation or updated after
creation.

» Attributes Reference

The following attributes are exported:

- id ID of the router.
- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- admin_state_up See Argument Reference above.
- external_gateway See Argument Reference above.
- external_network_id See Argument Reference above.
- enable_snat See Argument Reference above.
- external_fixed_ip See Argument Reference above.
- tenant_id See Argument Reference above.
- $\bullet\,$ value_specs See Argument Reference above.
- availability_zone_hints See Argument Reference above.
- tags See Argument Reference above.
- all_tags The collection of tags assigned on the router, which have been explicitly and implicitly added.

» Import

Routers can be imported using the id, e.g.

\$ terraform import openstack_networking_router_v2.router_1 014395cd-89fc-4c9b-96b7-13d1ee79d

» openstack_networking_subnet_v2

Manages a V2 Neutron subnet resource within OpenStack.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron subnet. If omitted, the region argument of the provider is used. Changing this creates a new subnet.
- network_id (Required) The UUID of the parent network. Changing this creates a new subnet.
- cidr (Optional) CIDR representing IP range for this subnet, based on IP version. You can omit this option if you are creating a subnet from a subnet pool.
- ip_version (Optional) IP version, either 4 (default) or 6. Changing this creates a new subnet.
- ipv6_address_mode (Optional) The IPv6 address mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- ipv6_ra_mode (Optional) The IPv6 Router Advertisement mode. Valid values are dhcpv6-stateful, dhcpv6-stateless, or slaac.
- name (Optional) The name of the subnet. Changing this updates the name of the existing subnet.
- description (Optional) Human-readable description of the subnet. Changing this updates the name of the existing subnet.

- tenant_id (Optional) The owner of the subnet. Required if admin wants to create a subnet for another tenant. Changing this creates a new subnet.
- allocation_pools (Optional) An array of sub-ranges of CIDR available for dynamic allocation to ports. The allocation_pool object structure is documented below. Changing this creates a new subnet.
- gateway_ip (Optional) Default gateway used by devices in this subnet. Leaving this blank and not setting no_gateway will cause a default gateway of .1 to be used. Changing this updates the gateway IP of the existing subnet.
- no_gateway (Optional) Do not set a gateway IP on this subnet. Changing this removes or adds a default gateway IP of the existing subnet.
- enable_dhcp (Optional) The administrative state of the network. Acceptable values are "true" and "false". Changing this value enables or disables the DHCP capabilities of the existing subnet. Defaults to true.
- dns_nameservers (Optional) An array of DNS name server names used by hosts in this subnet. Changing this updates the DNS name servers for the existing subnet.
- host_routes (Deprecated use openstack_networking_subnet_route_v2 instead) An array of routes that should be used by devices with IPs from this subnet (not including local subnet route). The host_route object structure is documented below. Changing this updates the host routes for the existing subnet.
- subnetpool_id (Optional) The ID of the subnetpool associated with the subnet.
- value_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the subnet.

The allocation_pools block supports:

- start (Required) The starting address.
- end (Required) The ending address.

The host_routes block supports:

- destination_cidr (Required) The destination CIDR.
- next_hop (Required) The next hop in the route.

» Attributes Reference

The following attributes are exported:

• region - See Argument Reference above.

- network_id See Argument Reference above.
- cidr See Argument Reference above.
- ip_version See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- tenant_id See Argument Reference above.
- allocation_pools See Argument Reference above.
- gateway_ip See Argument Reference above.
- enable_dhcp See Argument Reference above.
- dns_nameservers See Argument Reference above.
- host_routes See Argument Reference above.
- subnetpool_id See Argument Reference above.
- tags See Argument Reference above.
- all_tags The collection of ags assigned on the subnet, which have been explicitly and implicitly added.

» Import

Subnets can be imported using the id, e.g.

» openstack networking subnet route v2

Creates a routing entry on a OpenStack V2 subnet.

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to configure a routing entry on a subnet. If omitted, the region argument of the provider is used. Changing this creates a new routing entry.
- subnet_id (Required) ID of the subnet this routing entry belongs to. Changing this creates a new routing entry.
- destination_cidr (Required) CIDR block to match on the packet's destination IP. Changing this creates a new routing entry.
- next_hop (Required) IP address of the next hop gateway. Changing this creates a new routing entry.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- subnet_id See Argument Reference above.
- destination cidr See Argument Reference above.
- next_hop See Argument Reference above.

» Notes

» Import

Routing entries can be imported using a combined ID using the following format: <subnet_id>-route-<destination_cidr>-<next_hop>

\$ terraform import openstack_networking_subnet_route_v2.subnet_route_1 686fe248-386c-4f70-9:

» openstack_networking_subnetpool_v2

Manages a V2 Neutron subnetpool resource within OpenStack.

» Example Usage

» Create a Subnet Pool

```
resource "openstack_networking_subnetpool_v2" "subnetpool_1" {
 name = "subnetpool_1"
  ip version = 6
 prefixes = ["fdf7:b13d:dead:beef::/64", "fd65:86cc:a334:39b7::/64"]
» Create a Subnet from a Subnet Pool
resource "openstack_networking_network_v2" "network_1" {
 name = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnetpool_v2" "subnetpool_1" {
 name = "subnetpool_1"
 prefixes = ["10.11.12.0/24"]
resource "openstack_networking_subnet_v2" "subnet_1" {
 name = "subnet 1"
 cidr = "10.11.12.0/25"
 network id = "${openstack networking network v2.network 1.id}"
  subnetpool_id = "${openstack_networking_subnetpool_v2.subnetpool_1.id}"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a Neutron subnetpool. If omitted, the region argument of the provider is used. Changing this creates a new subnetpool.
- name (Required) The name of the subnetpool. Changing this updates the name of the existing subnetpool.

- default_quota (Optional) The per-project quota on the prefix space that can be allocated from the subnetpool for project subnets. Changing this updates the default quota of the existing subnetpool.
- project_id (Optional) The owner of the subnetpool. Required if admin wants to create a subnetpool for another project. Changing this creates a new subnetpool.
- prefixes (Required) A list of subnet prefixes to assign to the subnetpool. Neutron API merges adjacent prefixes and treats them as a single prefix. Each subnet prefix must be unique among all subnet prefixes in all subnetpools that are associated with the address scope. Changing this updates the prefixes list of the existing subnetpool.
- default_prefixlen (Optional) The size of the prefix to allocate when the cidr or prefixlen attributes are omitted when you create the subnet. Defaults to the MinPrefixLen. Changing this updates the default prefixlen of the existing subnetpool.
- min_prefixlen (Optional) The smallest prefix that can be allocated from a subnetpool. For IPv4 subnetpools, default is 8. For IPv6 subnetpools, default is 64. Changing this updates the min prefixlen of the existing subnetpool.
- max_prefixlen (Optional) The maximum prefix size that can be allocated from the subnetpool. For IPv4 subnetpools, default is 32. For IPv6 subnetpools, default is 128. Changing this updates the max prefixlen of the existing subnetpool.
- address_scope_id (Optional) The Neutron address scope to assign to the subnetpool. Changing this updates the address scope id of the existing subnetpool.
- shared (Optional) Indicates whether this subnetpool is shared across all
 projects. Changing this updates the shared status of the existing subnetpool.
- description (Optional) The human-readable description for the subnetpool. Changing this updates the description of the existing subnetpool.
- is_default (Optional) Indicates whether the subnetpool is default subnetpool or not. Changing this updates the default status of the existing subnetpool.
- value_specs (Optional) Map of additional options.
- tags (Optional) A set of string tags for the subnetpool.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- default_quota See Argument Reference above.
- project_id See Argument Reference above.
- created_at The time at which subnetpool was created.
- updated_at The time at which subnetpool was created.
- prefixes See Argument Reference above.
- default_prefixlen See Argument Reference above.
- min_prefixlen See Argument Reference above.
- max_prefixlen See Argument Reference above.
- address_scope_id See Argument Reference above.
- ip_version The IP protocol version.
- shared See Argument Reference above.
- description See Argument Reference above.
- is_default See Argument Reference above.
- revision_number The revision number of the subnetpool.
- value_specs See Argument Reference above.
- tags See Argument Reference above.
- all_tags The collection of tags assigned on the subnetpool, which have been explicitly and implicitly added.

» Import

Subnetpools can be imported using the id, e.g.

\$ terraform import openstack_networking_subnetpool_v2.subnetpool_1 832cb7f3-59fe-40cf-8f64-8

${\tt "openstack_networking_secgroup_v2}$

Manages a V2 neutron security group resource within OpenStack. Unlike Nova security groups, neutron separates the group from the rules and also allows an admin to target a specific tenant_id.

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new security group.
- name (Required) A unique name for the security group.
- description (Optional) A unique name for the security group.
- tenant_id (Optional) The owner of the security group. Required if admin wants to create a port for another tenant. Changing this creates a new security group.
- delete_default_rules (Optional) Whether or not to delete the default egress security rules. This is false by default. See the below note for more information.
- tags (Optional) A set of string tags for the security group.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- tenant_id See Argument Reference above.
- tags See Argument Reference above.
- all_tags The collection of tags assigned on the security group, which
 have been explicitly and implicitly added.

» Default Security Group Rules

In most cases, OpenStack will create some egress security group rules for each new security group. These security group rules will not be managed by Terraform, so if you prefer to have *all* aspects of your infrastructure managed by Terraform, set delete_default_rules to true and then create separate security group rules such as the following:

```
resource "openstack_networking_secgroup_rule_v2" "secgroup_rule_v4" {
   direction = "egress"
   ethertype = "IPv4"
   security_group_id = "${openstack_networking_secgroup_v2.secgroup.id}"
}
```

```
resource "openstack_networking_secgroup_rule_v2" "secgroup_rule_v6" {
   direction = "egress"
   ethertype = "IPv6"
   security_group_id = "${openstack_networking_secgroup_v2.secgroup.id}"
}
```

Please note that this behavior may differ depending on the configuration of the OpenStack cloud. The above illustrates the current default Neutron behavior. Some OpenStack clouds might provide additional rules and some might not provide any rules at all (in which case the delete_default_rules setting is moot).

» Import

Security Groups can be imported using the id, e.g.

\$ terraform import openstack_networking_secgroup_v2.secgroup_1 38809219-5e8a-4852-9139-6f46

» openstack_networking_secgroup_rule_v2

Manages a V2 neutron security group rule resource within OpenStack. Unlike Nova security groups, neutron separates the group from the rules and also allows an admin to target a specific tenant_id.

```
resource "openstack_networking_secgroup_v2" "secgroup_1" {
             = "secgroup_1"
  description = "My neutron security group"
resource "openstack_networking_secgroup_rule_v2" "secgroup_rule_1" {
  direction
                   = "ingress"
  ethertype
                   = "IPv4"
                   = "tcp"
 protocol
                 = 22
 port_range_min
 port_range_max
 remote_ip_prefix = "0.0.0.0/0"
  security_group_id = "${openstack_networking_secgroup_v2.secgroup_1.id}"
}
```

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a port. If omitted, the region argument of the provider is used. Changing this creates a new security group rule.
- description (Optional) A description of the rule. Changing this creates a new security group rule.
- direction (Required) The direction of the rule, valid values are **ingress** or **egress**. Changing this creates a new security group rule.
- ethertype (Required) The layer 3 protocol type, valid values are **IPv4** or **IPv6**. Changing this creates a new security group rule.
- protocol (Optional) The layer 4 protocol type, valid values are following. Changing this creates a new security group rule. This is required if you want to specify a port range.
 - tcp
 - udp
 - icmp
 - ah
 - dccp
 - egp
 - esp
 - gre
 - igmp
 - ipv6-encap
 - ipv6-frag
 - ipv6-icmp
 - ipv6-nonxt
 - ipv6-opts
 - ipv6-route
 - ospf
 - pgm
 - rsvp
 - sctp
 - udplite
 - vrrp
- port_range_min (Optional) The lower part of the allowed port range, valid integer value needs to be between 1 and 65535. Changing this creates a new security group rule.
- port_range_max (Optional) The higher part of the allowed port range,

valid integer value needs to be between 1 and 65535. Changing this creates a new security group rule.

- remote_ip_prefix (Optional) The remote CIDR, the value needs to be a valid CIDR (i.e. 192.168.0.0/16). Changing this creates a new security group rule.
- remote_group_id (Optional) The remote group id, the value needs to be an Openstack ID of a security group in the same tenant. Changing this creates a new security group rule.
- security_group_id (Required) The security group id the rule should belong to, the value needs to be an Openstack ID of a security group in the same tenant. Changing this creates a new security group rule.
- tenant_id (Optional) The owner of the security group. Required if admin wants to create a port for another tenant. Changing this creates a new security group rule.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- description See Argument Reference above.
- direction See Argument Reference above.
- ethertype See Argument Reference above.
- protocol See Argument Reference above.
- port_range_min See Argument Reference above.
 port range max See Argument Reference above.
- remote_ip_prefix See Argument Reference above.
- remote_group_id See Argument Reference above.
- security_group_id See Argument Reference above.
- bootify_61oup_1a See Highment Reference of
- tenant_id See Argument Reference above.

» Import

Security Group Rules can be imported using the id, e.g.

\$ terraform import openstack_networking_secgroup_rule_v2.secgroup_rule_1 aeb68ee3-6e9d-4256-

» openstack_networking_trunk_v2

Manages a networking V2 trunk resource within OpenStack.

```
resource "openstack_networking_network_v2" "network_1" {
 name = "network_1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
 name = "subnet 1"
 network_id = "${openstack_networking_network_v2.network_1.id}"
 cidr = "192.168.1.0/24"
 ip_version = 4
  enable_dhcp = true
 no_gateway = true
}
resource "openstack_networking_port_v2" "parent_port_1" {
  depends_on = [
   "openstack_networking_subnet_v2.subnet_1",
 name = "parent_port_1"
 network_id = "${openstack_networking_network_v2.network_1.id}"
  admin_state_up = "true"
}
resource "openstack_networking_port_v2" "subport_1" {
  depends_on = [
    "openstack_networking_subnet_v2.subnet_1",
 ]
 name = "subport_1"
 network_id = "${openstack_networking_network_v2.network_1.id}"
  admin_state_up = "true"
resource "openstack_networking_trunk_v2" "trunk_1" {
 name = "trunk_1"
  admin_state_up = "true"
 port_id = "${openstack_networking_port_v2.parent_port_1.id}"
  sub_port {
    port_id = "${openstack_networking_port_v2.subport_1.id}"
    segmentation_id = 1
    segmentation_type = "vlan"
```

```
}
}
resource "openstack_compute_instance_v2" "instance_1" {
  name = "instance_1"
  security_groups = ["default"]

network {
  port = "${openstack_networking_trunk_v2.trunk_1.port_id}"
  }
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 networking client. A networking client is needed to create a trunk. If omitted, the region argument of the provider is used. Changing this creates a new trunk.
- name (Optional) A unique name for the trunk. Changing this updates the name of an existing trunk.
- description (Optional) Human-readable description of the trunk. Changing this updates the name of the existing trunk.
- port_id (Required) The ID of the port to be used as the parent port of the trunk. This is the port that should be used as the compute instance network port. Changing this creates a new trunk.
- admin_state_up (Optional) Administrative up/down status for the trunk (must be "true" or "false" if provided). Changing this updates the admin_state_up of an existing trunk.
- tenant_id (Optional) The owner of the Trunk. Required if admin wants to create a trunk on behalf of another tenant. Changing this creates a new trunk.
- sub_port (Optional) The set of ports that will be made subports of the trunk. The structure of each subport is described below.
- tags (Optional) A set of string tags for the port.

The sub_port block supports:

• port_id - (Required) The ID of the port to be made a subport of the trunk.

- segmentation_type (Required) The segmentation technology to use, e.g., "vlan".
- segmentation_id (Required) The numeric id of the subport segment.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- port_id See Argument Reference above.
- admin_state_up See Argument Reference above.
- tenant_id See Argument Reference above.
- sub_port See Argument Reference above.
- tags See Argument Reference above.
- all_tags The collection of tags assigned on the trunk, which have been explicitly and implicitly added.

» openstack_lb_member_v1

Manages a V1 load balancer member resource within OpenStack.

» Example Usage

```
resource "openstack_lb_member_v1" "member_1" {
  pool_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"
  address = "192.168.0.10"
  port = 80
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB member. If omitted, the region argument of the provider is used. Changing this creates a new LB member.
- pool_id (Required) The ID of the LB pool. Changing this creates a new member.

- address (Required) The IP address of the member. Changing this creates a new member.
- port (Required) An integer representing the port on which the member is hosted. Changing this creates a new member.
- admin_state_up (Optional) The administrative state of the member. Acceptable values are 'true' and 'false'. Changing this value updates the state of the existing member.
- tenant_id (Optional) The owner of the member. Required if admin wants to create a member for another tenant. Changing this creates a new member.

The following attributes are exported:

- region See Argument Reference above.
- pool_id See Argument Reference above.
- address See Argument Reference above.
- port See Argument Reference above.
- admin_state_up See Argument Reference above.
- weight The load balancing weight of the member. This is currently unable to be set through Terraform.

» Import

Load Balancer Members can be imported using the id, e.g.

\$ terraform import openstack_lb_member_v1.member_1 a7498676-4fe4-4243-a864-2eaaf18c73df

ightarrow openstack_lb_monitor_v1

Manages a V1 load balancer monitor resource within OpenStack.

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB monitor. If omitted, the region argument of the provider is used. Changing this creates a new LB monitor.
- type (Required) The type of probe, which is PING, TCP, HTTP, or HTTPS, that is sent by the monitor to verify the member state. Changing this creates a new monitor.
- delay (Required) The time, in seconds, between sending probes to members. Changing this creates a new monitor.
- timeout (Required) Maximum number of seconds for a monitor to wait for a ping reply before it times out. The value must be less than the delay value. Changing this updates the timeout of the existing monitor.
- max_retries (Required) Number of permissible ping failures before changing the member's status to INACTIVE. Must be a number between 1 and 10. Changing this updates the max retries of the existing monitor.
- url_path (Optional) Required for HTTP(S) types. URI path that will be accessed if monitor type is HTTP or HTTPS. Changing this updates the url_path of the existing monitor.
- http_method (Optional) Required for HTTP(S) types. The HTTP method used for requests by the monitor. If this attribute is not specified, it defaults to "GET". Changing this updates the http_method of the existing monitor.
- expected_codes (Optional) Required for HTTP(S) types. Expected HTTP codes for a passing HTTP(S) monitor. You can either specify a single status like "200", or a range like "200-202". Changing this updates the expected codes of the existing monitor.
- admin_state_up (Optional) The administrative state of the monitor. Acceptable values are "true" and "false". Changing this value updates the state of the existing monitor.
- tenant_id (Optional) The owner of the monitor. Required if admin wants to create a monitor for another tenant. Changing this creates a new monitor.

The following attributes are exported:

- region See Argument Reference above.
- type See Argument Reference above.
- delay See Argument Reference above.
- timeout See Argument Reference above.
- max_retries See Argument Reference above.
- url_path See Argument Reference above.
- http_method See Argument Reference above.
- expected_codes See Argument Reference above.
- admin_state_up See Argument Reference above.
- tenant_id See Argument Reference above.

» Import

Load Balancer Members can be imported using the id, e.g.

```
$ terraform import openstack_lb_monitor_v1.monitor_1 119d7530-72e9-449a-aa97-124a5ef1992c
```

» openstack_lb_pool_v1

Manages a V1 load balancer pool resource within OpenStack.

» Example Usage

» Complete Load Balancing Stack Example

```
resource "openstack_networking_subnet_v2" "subnet_1" {
 network_id = "${openstack_networking_network_v2.network_1.id}"
            = "192.168.199.0/24"
  ip\_version = 4
}
resource "openstack_compute_secgroup_v2" "secgroup_1" {
             = "secgroup_1"
  description = "Rules for secgroup_1"
 rule {
   from_port = -1
   to_port = -1
   ip_protocol = "icmp"
              = "0.0.0.0/0"
   cidr
 }
 rule {
    from_port = 80
   to_port = 80
    ip_protocol = "tcp"
              = "0.0.0.0/0"
    cidr
 }
}
\tt resource "openstack\_compute\_instance\_v2" "instance\_1" \ \{
                 = "instance_1"
  security_groups = ["default", "${openstack_compute_secgroup_v2.secgroup_1.name}"]
 network {
   uuid = "${openstack_networking_network_v2.network_1.id}"
 }
}
resource "openstack_compute_instance_v2" "instance_2" {
                 = "instance_2"
  security_groups = ["default", "${openstack_compute_secgroup_v2.secgroup_1.name}"]
 network {
    uuid = "${openstack_networking_network_v2.network_1.id}"
 }
}
resource "openstack_lb_monitor_v1" "monitor_1" {
                = "TCP"
  type
```

```
= 30
 delay
                = 5
 timeout
 max retries
                = 3
 admin_state_up = "true"
}
resource "openstack_lb_pool_v1" "pool_1" {
             = "pool_1"
 name
             = "TCP"
 protocol
 subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
 lb method = "ROUND ROBIN"
 monitor_ids = ["${openstack_lb_monitor_v1.monitor_1.id}"]
}
resource "openstack_lb_member_v1" "member_1" {
 pool id = "${openstack lb pool v1.pool 1.id}"
 address = "${openstack_compute_instance_v2.instance_1.access_ip_v4}"
 port
         = 80
}
resource "openstack_lb_member_v1" "member_2" {
 pool_id = "${openstack_lb_pool_v1.pool_1.id}"
 address = "${openstack_compute_instance_v2.instance_2.access_ip_v4}"
 port
}
resource "openstack_lb_vip_v1" "vip_1" {
            = "vip 1"
 subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
 protocol = "TCP"
 port
            = 80
 pool_id
          = "${openstack_lb_pool_v1.pool_1.id}"
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB pool. If omitted, the region argument of the provider is used. Changing this creates a new LB pool.
- name (Required) The name of the pool. Changing this updates the name of the existing pool.

- protocol (Required) The protocol used by the pool members, you can use either 'TCP, 'HTTP', or 'HTTPS'. Changing this creates a new pool.
- subnet_id (Required) The network on which the members of the pool will be located. Only members that are on this network can be added to the pool. Changing this creates a new pool.
- 1b_method (Required) The algorithm used to distribute load between the members of the pool. The current specification supports 'ROUND_ROBIN' and 'LEAST_CONNECTIONS' as valid values for this attribute.
- lb_provider (Optional) The backend load balancing provider. For example: haproxy, F5, etc.
- tenant_id (Optional) The owner of the pool. Required if admin wants to create a pool member for another tenant. Changing this creates a new pool.
- monitor_ids (Optional) A list of IDs of monitors to associate with the pool.
- member (Optional) An existing node to add to the pool. Changing this updates the members of the pool. The member object structure is documented below. Please note that the member block is deprecated in favor of the openstack_lb_member_v1 resource.

The member block supports:

- address (Required) The IP address of the member. Changing this creates a new member.
- port (Required) An integer representing the port on which the member is hosted. Changing this creates a new member.
- admin_state_up (Required) The administrative state of the member. Acceptable values are 'true' and 'false'. Changing this value updates the state of the existing member.
- tenant_id (Optional) The owner of the member. Required if admin wants to create a pool member for another tenant. Changing this creates a new member.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- protocol See Argument Reference above.
- subnet_id See Argument Reference above.

- 1b_method See Argument Reference above.
- lb_provider See Argument Reference above.
- tenant_id See Argument Reference above.
- monitor_id See Argument Reference above.
- member See Argument Reference above.

» Notes

The member block is deprecated in favor of the openstack_lb_member_v1 resource.

» Import

Load Balancer Pools can be imported using the id, e.g.

```
$ terraform import openstack_lb_pool_v1.pool_1 b255e6ba-02ad-43e6-8951-3428ca26b713
```

» openstack_lb_vip_v1

Manages a V1 load balancer vip resource within OpenStack.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VIP. If omitted, the region argument of the provider is used. Changing this creates a new VIP.
- name (Required) The name of the vip. Changing this updates the name of the existing vip.

- subnet_id (Required) The network on which to allocate the vip's address. A tenant can only create vips on networks authorized by policy (e.g. networks that belong to them or networks that are shared). Changing this creates a new vip.
- protocol (Required) The protocol can be either 'TCP, 'HTTP', or HTTPS'. Changing this creates a new vip.
- port (Required) The port on which to listen for client traffic. Changing this creates a new vip.
- pool_id (Required) The ID of the pool with which the vip is associated. Changing this updates the pool_id of the existing vip.
- tenant_id (Optional) The owner of the vip. Required if admin wants to create a vip member for another tenant. Changing this creates a new vip.
- address (Optional) The IP address of the vip. Changing this creates a new vip.
- description (Optional) Human-readable description for the vip. Changing this updates the description of the existing vip.
- persistence (Optional) Omit this field to prevent session persistence. The persistence object structure is documented below. Changing this updates the persistence of the existing vip.
- conn_limit (Optional) The maximum number of connections allowed for the vip. Default is -1, meaning no limit. Changing this updates the conn limit of the existing vip.
- floating_ip (Optional) A Networking Floating IP that will be associated with the vip. The Floating IP must be provisioned already.
- admin_state_up (Optional) The administrative state of the vip. Acceptable values are "true" and "false". Changing this value updates the state of the existing vip.

The persistence block supports:

- type (Required) The type of persistence mode. Valid values are "SOURCE_IP", "HTTP_COOKIE", or "APP_COOKIE".
- cookie_name (Optional) The name of the cookie if persistence mode is set appropriately.

» Attributes Reference

The following attributes are exported:

• region - See Argument Reference above.

- name See Argument Reference above.
- subnet_id See Argument Reference above.
- protocol See Argument Reference above.
- port See Argument Reference above.
- pool_id See Argument Reference above.
- tenant_id See Argument Reference above.
- address See Argument Reference above.
- description See Argument Reference above.
- persistence See Argument Reference above.
- conn_limit See Argument Reference above.
- floating_ip See Argument Reference above.
- admin_state_up See Argument Reference above.
- port_id Port UUID for this VIP at associated floating IP (if any).

» Import

Load Balancer VIPs can be imported using the id, e.g.

\$ terraform import openstack_lb_vip_v1.vip_1 50e16b26-89c1-475e-a492-76167182511e

» openstack_lb_loadbalancer_v2

Manages a V2 loadbalancer resource within OpenStack.

» Example Usage

```
resource "openstack_lb_loadbalancer_v2" "lb_1" {
   vip_subnet_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an LB member. If omitted, the region argument of the provider is used. Changing this creates a new LB member.
- vip_subnet_id (Required) The network on which to allocate the Load-balancer's address. A tenant can only create Loadbalancers on networks authorized by policy (e.g. networks that belong to them or networks that are shared). Changing this creates a new loadbalancer.

- name (Optional) Human-readable name for the Loadbalancer. Does not have to be unique.
- description (Optional) Human-readable description for the Loadbal-ancer.
- tenant_id-(Optional) Required for admins. The UUID of the tenant who owns the Loadbalancer. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new loadbalancer.
- vip_address (Optional) The ip address of the load balancer. Changing this creates a new loadbalancer.
- admin_state_up (Optional) The administrative state of the Loadbalancer. A valid value is true (UP) or false (DOWN).
- flavor (Optional) The UUID of a flavor. Changing this creates a new loadbalancer.
- loadbalancer_provider (Optional) The name of the provider. Changing this creates a new loadbalancer.
- security_group_ids (Optional) A list of security group IDs to apply to the loadbalancer. The security groups must be specified by ID and not name (as opposed to how they are configured with the Compute Instance).

The following attributes are exported:

- region See Argument Reference above.
- vip_subnet_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- tenant_id See Argument Reference above.
- vip_address See Argument Reference above.
- admin_state_up See Argument Reference above.
- flavor See Argument Reference above.
- loadbalancer_provider See Argument Reference above.
- security_group_ids See Argument Reference above.
- vip_port_id The Port ID of the Load Balancer IP.

» Import

Load Balancer can be imported using the Load Balancer ID, e.g.:

\$ terraform import openstack_lb_loadbalancer_v2.loadbalancer_1 19bcfdc7-c521-4a7e-9459-67500

» openstack_lb_listener_v2

Manages a V2 listener resource within OpenStack.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new Listener.
- protocol (Required) The protocol can either be TCP, HTTP, HTTPS or TERMINATED_HTTPS. Changing this creates a new Listener.
- protocol_port (Required) The port on which to listen for client traffic. Changing this creates a new Listener.
- tenant_id (Optional) Required for admins. The UUID of the tenant who owns the Listener. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new Listener.
- loadbalancer_id (Required) The load balancer on which to provision this Listener. Changing this creates a new Listener.
- name (Optional) Human-readable name for the Listener. Does not have to be unique.
- default_pool_id (Optional) The ID of the default pool with which the Listener is associated.
- description (Optional) Human-readable description for the Listener.
- connection_limit (Optional) The maximum number of connections allowed for the Listener.
- default_tls_container_ref (Optional) A reference to a Barbican Secrets container which stores TLS information. This is required if the protocol is TERMINATED_HTTPS. See here for more information.

- sni_container_refs (Optional) A list of references to Barbican Secrets containers which store SNI information. See here for more information.
- admin_state_up (Optional) The administrative state of the Listener. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the Listener.
- protocol See Argument Reference above.
- protocol_port See Argument Reference above.
- tenant_id See Argument Reference above.
- name See Argument Reference above.
- default_port_id See Argument Reference above.
- description See Argument Reference above.
- connection_limit See Argument Reference above.
- default_tls_container_ref See Argument Reference above.
- sni_container_refs See Argument Reference above.
- admin_state_up See Argument Reference above.

» Import

Load Balancer Listener can be imported using the Listener ID, e.g.:

\$ terraform import openstack_lb_listener_v2.listener_1 b67ce64e-8b26-405d-afeb-4a078901f15a

$ightsymbol{"} openstack_lb_pool_v2$

Manages a V2 pool resource within OpenStack.

```
resource "openstack_lb_pool_v2" "pool_1" {
  protocol = "HTTP"
  lb_method = "ROUND_ROBIN"
  listener_id = "d9415786-5f1a-428b-b35f-2f1523e146d2"

persistence {
  type = "HTTP_COOKIE"
  cookie_name = "testCookie"
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new pool.
- tenant_id (Optional) Required for admins. The UUID of the tenant who owns the pool. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new pool.
- name (Optional) Human-readable name for the pool.
- description (Optional) Human-readable description for the pool.
- protocol = (Required) The protocol can either be TCP, HTTP, HTTPS or PROXY. Changing this creates a new pool.
- loadbalancer_id (Optional) The load balancer on which to provision this pool. Changing this creates a new pool. Note: One of LoadbalancerID or ListenerID must be provided.
- listener_id (Optional) The Listener on which the members of the pool will be associated with. Changing this creates a new pool. Note: One of LoadbalancerID or ListenerID must be provided.
- 1b_method (Required) The load balancing algorithm to distribute traffic to the pool's members. Must be one of ROUND_ROBIN, LEAST CONNECTIONS, or SOURCE IP.
- persistence Omit this field to prevent session persistence. Indicates whether connections in the same session will be processed by the same Pool member or not. Changing this creates a new pool.
- admin_state_up (Optional) The administrative state of the pool. A valid value is true (UP) or false (DOWN).

The persistence argument supports:

- type (Required) The type of persistence mode. The current specification supports SOURCE_IP, HTTP_COOKIE, and APP_COOKIE.
- cookie_name (Optional) The name of the cookie if persistence mode is set appropriately. Required if type = APP_COOKIE.

The following attributes are exported:

- id The unique ID for the pool.
- tenant_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- protocol See Argument Reference above.
- 1b_method See Argument Reference above.
- persistence See Argument Reference above.
- admin_state_up See Argument Reference above.

» Import

Load Balancer Pool can be imported using the Pool ID, e.g.:

```
$ terraform import openstack_lb_pool_v2.pool_1 60ad9ee4-249a-4d60-a45b-aa60e046c513
```

» openstack_lb_member_v2

Manages a V2 member resource within OpenStack.

» Example Usage

```
resource "openstack_lb_member_v2" "member_1" {
  address = "192.168.199.23"
  protocol_port = 8080
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new member.
- pool_id (Required) The id of the pool that this member will be assigned to.
- subnet_id (Optional) The subnet in which to access the member
- name (Optional) Human-readable name for the member.

- tenant_id (Optional) Required for admins. The UUID of the tenant who owns the member. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new member.
- address (Required) The IP address of the member to receive traffic from the load balancer. Changing this creates a new member.
- protocol_port (Required) The port on which to listen for client traffic. Changing this creates a new member.
- weight (Optional) A positive integer value that indicates the relative portion of traffic that this member should receive from the pool. For example, a member with a weight of 10 receives five times as much traffic as a member with a weight of 2.
- admin_state_up (Optional) The administrative state of the member. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the member.
- name See Argument Reference above.
- weight See Argument Reference above.
- admin_state_up See Argument Reference above.
- tenant_id See Argument Reference above.
- subnet_id See Argument Reference above.
- pool_id See Argument Reference above.
- address See Argument Reference above.
- protocol_port See Argument Reference above.

» Import

Load Balancer Pool Member can be imported using the Pool ID and Member ID separated by a slash. e.g.:

\$ terraform import openstack_lb_member_v2.member_1 c22974d2-4c95-4bcb-9819-0afc5ed303d5/956

$ightsymbol{"} openstack_lb_monitor_v2$

Manages a V2 monitor resource within OpenStack.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new monitor.
- pool_id (Required) The id of the pool that this monitor will be assigned to.
- name (Optional) The Name of the Monitor.
- tenant_id (Optional) Required for admins. The UUID of the tenant who owns the monitor. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new monitor.
- type (Required) The type of probe, which is PING, TCP, HTTP, or HTTPS, that is sent by the load balancer to verify the member state. Changing this creates a new monitor.
- delay (Required) The time, in seconds, between sending probes to members.
- timeout (Required) Maximum number of seconds for a monitor to wait for a ping reply before it times out. The value must be less than the delay value.
- max_retries (Required) Number of permissible ping failures before changing the member's status to INACTIVE. Must be a number between 1 and 10..
- url_path (Optional) Required for HTTP(S) types. URI path that will be accessed if monitor type is HTTP or HTTPS.
- http_method (Optional) Required for HTTP(S) types. The HTTP method used for requests by the monitor. If this attribute is not specified, it defaults to "GET".

- expected_codes (Optional) Required for HTTP(S) types. Expected HTTP codes for a passing HTTP(S) monitor. You can either specify a single status like "200", or a range like "200-202".
- admin_state_up (Optional) The administrative state of the monitor. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the monitor.
- tenant_id See Argument Reference above.
- type See Argument Reference above.
- delay See Argument Reference above.
- timeout See Argument Reference above.
- max_retries See Argument Reference above.
- url_path See Argument Reference above.
- http_method See Argument Reference above.
- expected_codes See Argument Reference above.
- admin_state_up See Argument Reference above.

» Import

Load Balancer Pool Monitor can be imported using the Monitor ID, e.g.:

\$ terraform import openstack_lb_monitor_v2.monitor_1 47c26fc3-2403-427a-8c79-1589bd0533c2

» openstack_lb_l7policy_v2

Manages a Load Balancer L7 Policy resource within OpenStack.

```
resource "openstack_networking_network_v2" "network_1" {
  name = "network_1"
  admin_state_up = "true"
}

resource "openstack_networking_subnet_v2" "subnet_1" {
  name = "subnet_1"
  cidr = "192.168.199.0/24"
  ip_version = 4
```

```
network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_lb_loadbalancer_v2" "loadbalancer_1" {
 name = "loadbalancer_1"
  vip_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_lb_listener_v2" "listener_1" {
 name = "listener 1"
 protocol = "HTTP"
 protocol_port = 8080
  loadbalancer_id = "${openstack_lb_loadbalancer_v2.loadbalancer_1.id}"
}
resource "openstack_lb_pool_v2" "pool_1" {
 name
                 = "pool_1"
                 = "HTTP"
 protocol
                 = "ROUND_ROBIN"
 lb_method
  loadbalancer_id = "${openstack_lb_loadbalancer_v2.loadbalancer_1.id}"
}
resource "openstack_lb_17policy_v2" "17policy_1" {
                  = "test"
 name
                 = "REDIRECT_TO_POOL"
  action
 description = "test 17 policy"
                 = 1
 position
                  = "${openstack lb listener v2.listener 1.id}"
 listener id
  redirect_pool_id = "${openstack_lb_pool_v2.pool_1.id}"
}
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new L7 Policy.
- tenant_id (Optional) Required for admins. The UUID of the tenant who owns the L7 Policy. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new L7 Policy.
- name (Optional) Human-readable name for the L7 Policy. Does not have to be unique.
- description (Optional) Human-readable description for the L7 Policy.

- action (Required) The L7 Policy action can either be REDI-RECT_TO_POOL, REDIRECT_TO_URL or REJECT.
- listener_id (Required) The Listener on which the L7 Policy will be associated with. Changing this creates a new L7 Policy.
- position (Optional) The position of this policy on the listener. Positions start at 1.
- redirect_pool_id (Optional) Requests matching this policy will be redirected to the pool with this ID. Only valid if action is REDI-RECT_TO_POOL.
- redirect_url (Optional) Requests matching this policy will be redirected to this URL. Only valid if action is REDIRECT_TO_URL.
- admin_state_up (Optional) The administrative state of the L7 Policy. A valid value is true (UP) or false (DOWN).

The following attributes are exported:

- id The unique ID for the L7 {olicy.
- region See Argument Reference above.
- tenant_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- action See Argument Reference above.
- listener id See Argument Reference above.
- position See Argument Reference above.
- redirect_pool_id See Argument Reference above.
- redirect_url See Argument Reference above.
- admin_state_up See Argument Reference above.

» Import

Load Balancer L7 Policy can be imported using the L7 Policy ID, e.g.:

\$ terraform import openstack_lb_17policy_v2.17policy_1 8a7a79c2-cf17-4e65-b2ae-ddc8bfcf6c74

» openstack_lb_l7rule_v2

Manages a V2 L7 Rule resource within OpenStack.

```
resource "openstack_networking_network_v2" "network_1" {
 name = "network 1"
  admin_state_up = "true"
}
resource "openstack networking subnet v2" "subnet 1" {
 name = "subnet 1"
 cidr = "192.168.199.0/24"
 ip\_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_lb_loadbalancer_v2" "loadbalancer_1" {
 name = "loadbalancer_1"
  vip_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
resource "openstack_lb_listener_v2" "listener_1" {
 name = "listener 1"
 protocol = "HTTP"
 protocol_port = 8080
 loadbalancer_id = "${openstack_lb_loadbalancer_v2.loadbalancer_1.id}"
}
resource "openstack_lb_pool_v2" "pool_1" {
                 = "pool_1"
                 = "HTTP"
 protocol
                 = "ROUND_ROBIN"
 lb_method
 loadbalancer_id = "${openstack_lb_loadbalancer_v2.loadbalancer_1.id}"
}
resource "openstack_lb_17policy_v2" "17policy_1" {
              = "test"
             = "REDIRECT_TO_URL"
  action
 description = "test description"
 position
 listener_id = "${openstack_lb_listener_v2.listener_1.id}"
 redirect_url = "http://www.example.com"
}
resource "openstack_lb_17rule_v2" "17rule_1" {
  17policy_id = "${openstack_lb_17policy_v2.17policy_1.id}"
              = "PATH"
  type
```

```
compare_type = "EQUAL_TO"
value = "/api"
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an . If omitted, the region argument of the provider is used. Changing this creates a new L7 Rule.
- tenant_id (Optional) Required for admins. The UUID of the tenant who owns the L7 Rule. Only administrative users can specify a tenant UUID other than their own. Changing this creates a new L7 Rule.
- description (Optional) Human-readable description for the L7 Rule.
- type (Required) The L7 Rule type can either be COOKIE, FILE TYPE, HEADER, HOST NAME or PATH.
- compare_type (Required) The comparison type for the L7 rule can either be CONTAINS, STARTS_WITH, ENDS_WITH, EQUAL_TO or REGEX
- 17policy_id (Required) The ID of the L7 Policy to query. Changing this creates a new L7 Rule.
- value (Required) The value to use for the comparison. For example, the file type to compare.
- key (Optional) The key to use for the comparison. For example, the name of the cookie to evaluate. Valid when type is set to COOKIE or HEADER.
- invert (Optional) When true the logic of the rule is inverted. For example, with invert true, equal to would become not equal to. Default is false.
- admin_state_up (Optional) The administrative state of the L7 Rule. A
 valid value is true (UP) or false (DOWN).

» Attributes Reference

- id The unique ID for the L7 Rule.
- region See Argument Reference above.
- tenant_id See Argument Reference above.

- type See Argument Reference above.
- compare_type See Argument Reference above.
- 17policy_id See Argument Reference above.
- value See Argument Reference above.
- key See Argument Reference above.
- invert See Argument Reference above.
- admin_state_up See Argument Reference above.
- listener_id The ID of the Listener owning this resource.

Load Balancer L7 Rule can be imported using the L7 Policy ID and L7 Rule ID separated by a slash, e.g.:

\$ terraform import openstack_lb_17rule_v2.17rule_1 e0bd694a-abbe-450e-b329-0931fd1cc5eb/4086

» openstack_fw_firewall_v1

Manages a v1 firewall resource within OpenStack.

» Example Usage

```
resource "openstack_fw_rule_v1" "rule_1" {
               = "my-rule-1"
 name
               = "drop TELNET traffic"
 protocol = "tcp"
 destination_port = "23"
                = "true"
 enabled
}
resource "openstack_fw_rule_v1" "rule_2" {
             = "my-rule-2"
 description = "drop NTP traffic"
action = "dony"
               = "deny"
 action
 protocol = "udp"
 destination_port = "123"
                = "false"
 enabled
}
resource "openstack_fw_policy_v1" "policy_1" {
 name = "my-policy"
```

The following arguments are supported:

- region (Optional) The region in which to obtain the v1 networking client. A networking client is needed to create a firewall. If omitted, the region argument of the provider is used. Changing this creates a new firewall.
- policy_id (Required) The policy resource id for the firewall. Changing this updates the policy_id of an existing firewall.
- name (Optional) A name for the firewall. Changing this updates the name of an existing firewall.
- description (Required) A description for the firewall. Changing this updates the description of an existing firewall.
- admin_state_up (Optional) Administrative up/down status for the firewall (must be "true" or "false" if provided defaults to "true"). Changing this updates the admin state up of an existing firewall.
- tenant_id (Optional) The owner of the floating IP. Required if admin wants to create a firewall for another tenant. Changing this creates a new firewall.
- associated_routers (Optional) Router(s) to associate this firewall instance with. Must be a list of strings. Changing this updates the associated routers of an existing firewall. Conflicts with no_routers.
- no_routers (Optional) Should this firewall not be associated with any routers (must be "true" or "false" if provide defaults to "false"). Conflicts with associated_routers.
- value_specs (Optional) Map of additional options.

» Attributes Reference

- region See Argument Reference above.
- policy_id See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- admin_state_up See Argument Reference above.
- tenant_id See Argument Reference above.
- associated_routers See Argument Reference above.
- no_routers See Argument Reference above.

Firewalls can be imported using the id, e.g.

\$ terraform import openstack_fw_firewall_v1.firewall_1 c9e39fb2-ce20-46c8-a964-25f3898c7a97

» openstack_fw_policy_v1

Manages a v1 firewall policy resource within OpenStack.

» Example Usage

```
resource "openstack_fw_rule_v1" "rule_1" {
                 = "my-rule-1"
 name
                = "drop TELNET traffic"
 description
                = "deny"
 action
 protocol
             = "tcp"
 destination_port = "23"
                = "true"
  enabled
}
resource "openstack_fw_rule_v1" "rule_2" {
         = "my-rule-2"
 name
 description = "drop NTP traffic"
action = "deny"
 protocol = "udp"
 destination_port = "123"
                 = "false"
  enabled
resource "openstack_fw_policy_v1" "policy_1" {
 name = "my-policy"
 rules = ["${openstack_fw_rule_v1.rule_1.id}",
```

```
"${openstack_fw_rule_v1.rule_2.id}",
]
}
```

The following arguments are supported:

- region (Optional) The region in which to obtain the v1 networking client. A networking client is needed to create a firewall policy. If omitted, the region argument of the provider is used. Changing this creates a new firewall policy.
- name (Optional) A name for the firewall policy. Changing this updates the name of an existing firewall policy.
- description (Optional) A description for the firewall policy. Changing this updates the description of an existing firewall policy.
- rules (Optional) An array of one or more firewall rules that comprise the policy. Changing this results in adding/removing rules from the existing firewall policy.
- audited (Optional) Audit status of the firewall policy (must be "true" or "false" if provided defaults to "false"). This status is set to "false" whenever the firewall policy or any of its rules are changed. Changing this updates the audited status of an existing firewall policy.
- shared (Optional) Sharing status of the firewall policy (must be "true" or "false" if provided). If this is "true" the policy is visible to, and can be used in, firewalls in other tenants. Changing this updates the shared status of an existing firewall policy. Only administrative users can specify if the policy should be shared.
- value_specs (Optional) Map of additional options.

» Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- audited See Argument Reference above.
- shared See Argument Reference above.

Firewall Policies can be imported using the id, e.g.

\$ terraform import openstack_fw_policy_v1.policy_1 07f422e6-c596-474b-8b94-fe2c12506ce0

» openstack_fw_rule_v1

Manages a v1 firewall rule resource within OpenStack.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the v1 Compute client. A Compute client is needed to create a firewall rule. If omitted, the region argument of the provider is used. Changing this creates a new firewall rule.
- name (Optional) A unique name for the firewall rule. Changing this updates the name of an existing firewall rule.
- description (Optional) A description for the firewall rule. Changing this updates the description of an existing firewall rule.
- protocol (Required) The protocol type on which the firewall rule operates. Valid values are: tcp, udp, icmp, and any. Changing this updates the protocol of an existing firewall rule.
- action (Required) Action to be taken (must be "allow" or "deny") when the firewall rule matches. Changing this updates the action of an existing firewall rule.
- ip_version (Optional) IP version, either 4 (default) or 6. Changing this updates the ip_version of an existing firewall rule.

- source_ip_address (Optional) The source IP address on which the firewall rule operates. Changing this updates the source_ip_address of an existing firewall rule.
- destination_ip_address (Optional) The destination IP address on which the firewall rule operates. Changing this updates the destination_ip_address of an existing firewall rule.
- source_port (Optional) The source port on which the firewall rule operates. Changing this updates the source_port of an existing firewall rule.
- destination_port (Optional) The destination port on which the firewall rule operates. Changing this updates the destination_port of an existing firewall rule.
- enabled (Optional) Enabled status for the firewall rule (must be "true" or "false" if provided defaults to "true"). Changing this updates the enabled status of an existing firewall rule.
- tenant_id (Optional) The owner of the firewall rule. Required if admin wants to create a firewall rule for another tenant. Changing this creates a new firewall rule.
- value_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- description See Argument Reference above.
- protocol See Argument Reference above.
- action See Argument Reference above.
- ip_version See Argument Reference above.
- source_ip_address See Argument Reference above.
- destination_ip_address See Argument Reference above.
- source_port See Argument Reference above.
- destination_port See Argument Reference above.
- enabled See Argument Reference above.
- tenant_id See Argument Reference above.

» Import

Firewall Rules can be imported using the id, e.g.

\$ terraform import openstack fw rule v1.rule 1 8dbc0c28-e49c-463f-b712-5c5d1bbac327

» openstack_objectstorage_container_v1

Manages a V1 container resource within OpenStack.

» Example Usage

```
resource "openstack_objectstorage_container_v1" "container_1" {
   region = "RegionOne"
   name = "tf-test-container-1"

metadata = {
   test = "true"
  }

content_type = "application/json"

versioning {
   type = "versions"
   location = "tf-test-container-versions"
  }
}
```

» Argument Reference

- region (Optional) The region in which to create the container. If omitted, the region argument of the provider is used. Changing this creates a new container.
- name (Required) A unique name for the container. Changing this creates a new container.
- container_read (Optional) Sets an access control list (ACL) that grants read access. This header can contain a comma-delimited list of users that can read the container (allows the GET method for all objects in the container). Changing this updates the access control list read access.
- container_sync_to (Optional) The destination for container synchronization. Changing this updates container synchronization.
- container_sync_key (Optional) The secret key for container synchronization. Changing this updates container synchronization.
- container_write (Optional) Sets an ACL that grants write access. Changing this updates the access control list write access.

- versioning (Optional) Enable object versioning. The structure is described below.
- metadata (Optional) Custom key/value pairs to associate with the container. Changing this updates the existing container metadata.
- content_type (Optional) The MIME type for the container. Changing this updates the MIME type.
- force_destroy (Optional, Default:false) A boolean that indicates all objects should be deleted from the container so that the container can be destroyed without error. These objects are not recoverable.

The versioning block supports:

- type (Required) Versioning type which can be versions or history according to Openstack documentation.
- location (Required) Container in which versions will be stored.

» Attributes Reference

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- container_read See Argument Reference above.
- container_sync_to See Argument Reference above.
- container_sync_key See Argument Reference above.
- container_write See Argument Reference above.
- versioning See Argument Reference above.
- metadata See Argument Reference above.
- content_type See Argument Reference above.

» openstack_objectstorage_object_v1

Manages a V1 container object resource within OpenStack.

» Example Usage

» Example with simple content

```
resource "openstack_objectstorage_container_v1" "container_1" {
  region = "RegionOne"
  name = "tf-test-container-1"
```

```
metadata {
   test = "true"
 content_type = "application/json"
}
resource "openstack_objectstorage_object_v1" "doc_1" {
                = "RegionOne"
  container_name = "${openstack_objectstorage_container_v1.container_1.name}"
        = "test/default.json"
 metadata {
   test = "true"
 }
  content_type = "application/json"
  content = <<JSON</pre>
               "foo" : "bar"
JSON
}
» Example with content from file
resource "openstack_objectstorage_container_v1" "container_1" {
 region = "RegionOne"
 name = "tf-test-container-1"
 metadata {
   test = "true"
 content_type = "application/json"
}
resource "openstack_objectstorage_object_v1" "doc_1" {
                = "RegionOne"
 region
  container_name = "${openstack_objectstorage_container_v1.container_1.name}"
 name
              = "test/default.json"
 metadata {
   test = "true"
```

```
content_type = "application/json"
source = "./default.json"
}
```

- container_name (Required) A unique (within an account) name for the container. The container name must be from 1 to 256 characters long and can start with any character and contain any pattern. Character set must be UTF-8. The container name cannot contain a slash (/) character because this character delimits the container and object name. For example, the path /v1/account/www/pages specifies the www container, not the www/pages container.
- content (Optional) A string representing the content of the object. Conflicts with source and copy_from.
- content_disposition (Optional) A string which specifies the override behavior for the browser. For example, this header might specify that the browser use a download program to save this file rather than show the file, which is the default.
- content_encoding (Optional) A string representing the value of the Content-Encoding metadata.
- content_type (Optional) A string which sets the MIME type for the object.
- copy_from (Optional) A string representing the name of an object used to create the new object by copying the copy_from object. The value is in form {container}/{object}. You must UTF-8-encode and then URL-encode the names of the container and object before you include them in the header. Conflicts with source and content.
- delete_after (Optional) An integer representing the number of seconds after which the system removes the object. Internally, the Object Storage system stores this value in the X-Delete-At metadata item.
- delete_at (Optional) An string representing the date when the system removes the object. For example, "2015-08-26" is equivalent to Mon, Wed, 26 Aug 2015 00:00:00 GMT.
- detect_content_type (Optional) If set to true, Object Storage guesses the content type based on the file extension and ignores the value sent in the Content-Type header, if present.
- etag (Optional) Used to trigger updates. The only meaningful value is ${\rm Md5(file("path/to/file"))}$.

- name (Required) A unique name for the object.
- object_manifest (Optional) A string set to specify that this is a dynamic large object manifest object. The value is the container and object name prefix of the segment objects in the form container/prefix. You must UTF-8-encode and then URL-encode the names of the container and prefix before you include them in this header.
- region (Optional) The region in which to create the container. If omitted, the region argument of the provider is used. Changing this creates a new container.
- source (Optional) A string representing the local path of a file which will be used as the object's content. Conflicts with source and copy_from.

- content_length If the operation succeeds, this value is zero (0) or the length of informational or error text in the response body.
- content_type If the operation succeeds, this value is the MIME type of the object. If the operation fails, this value is the MIME type of the error text in the response body.
- date The date and time the system responded to the request, using the preferred format of RFC 7231 as shown in this example Thu, 16 Jun 2016 15:10:38 GMT. The time is always in UTC.
- etag Whatever the value given in argument, will be overriden by the MD5 checksum of the uploaded object content. The value is not quoted. If it is an SLO, it would be MD5 checksum of the segments' etags.
- last_modified The date and time when the object was last modified. The date and time stamp format is ISO 8601: CCYY-MM-DDThh:mm:ss±hh:mm For example, 2015-08-27T09:49:58-05:00. The ±hh:mm value, if included, is the time zone as an offset from UTC. In the previous example, the offset value is -05:00.
- static_large_object True if object is a multipart_manifest.
- trans_id A unique transaction ID for this request. Your service provider might need this value if you report a problem.
- container_name See Argument Reference above.
- content See Argument Reference above.
- content disposition See Argument Reference above.
- content_encoding See Argument Reference above.

- copy_from See Argument Reference above.
- delete_after See Argument Reference above.
- delete_at See Argument Reference above.
- detect_content_type See Argument Reference above.
- name See Argument Reference above.
- object_manifest See Argument Reference above.
- region See Argument Reference above.
- source See Argument Reference above.

» openstack_objectstorage_tempurl_v1

Use this resource to generate an OpenStack Object Storage temporary URL.

The temporary URL will be valid for as long as TTL is set to (in seconds). Once the URL has expired, it will no longer be valid, but the resource will remain in place. If you wish to automatically regenerate a URL, set the regenerate argument to true. This will create a new resource with a new ID and URL.

» Example Usage

```
resource "openstack_objectstorage_tempurl_v1" "obj_tempurl" {
  container = "test"
  object = "container"
  method = "post"
  ttl = 20
}
```

» Argument Reference

- region (Optional) The region the tempurl is located in.
- container (Required) The container name the object belongs to.
- object (Required) The object name the tempurl is for.
- ttl (Required) The TTL, in seconds, for the URL. For how long it should be valid.
- method (Optional) The method allowed when accessing this URL. Valid values are GET, and POST. Default is GET.

• regenerate - (Optional) Whether to automatically regenerate the URL when it has expired. If set to true, this will create a new resource with a new ID and new URL. Defaults to false.

» Attributes Reference

- id Computed md5 hash based on the generated url
- container See Argument Reference above.
- object See Argument Reference above.
- ttl See Argument Reference above.
- method See Argument Reference above.
- url The URL
- region The region the endpoint is located in.

» openstack_vpnaas_ipsec_policy_v2

Manages a V2 Neutron IPSec policy resource within OpenStack.

» Example Usage

```
resource "openstack_vpnaas_ipsec_policy_v2" "policy_1" {
  name = "my_policy"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an IPSec policy. If omitted, the region argument of the provider is used. Changing this creates a new policy.
- name (Optional) The name of the policy. Changing this updates the name of the existing policy.
- tenant_id (Optional) The owner of the policy. Required if admin wants to create a policy for another project. Changing this creates a new policy.
- description (Optional) The human-readable description for the policy. Changing this updates the description of the existing policy.

- auth_algorithm (Optional) The authentication hash algorithm. Valid values are sha1, sha256, sha384, sha512. Default is sha1. Changing this updates the algorithm of the existing policy.
- encapsulation_mode (Optional) The encapsulation mode. Valid values are tunnel and transport. Default is tunnel. Changing this updates the existing policy.
- encryption_algorithm (Optional) The encryption algorithm. Valid values are 3des, aes-128, aes-192 and so on. The default value is aes-128. Changing this updates the existing policy.
- pfs (Optional) The perfect forward secrecy mode. Valid values are Group2, Group5 and Group14. Default is Group5. Changing this updates the existing policy.
- transform_protocol (Optional) The transform protocol. Valid values are ESP, AH and AH-ESP. Changing this updates the existing policy. Default is ESP.
- lifetime (Optional) The lifetime of the security association. Consists of Unit and Value.
 - unit (Optional) The units for the lifetime of the security association.
 Can be either seconds or kilobytes. Default is seconds.
 - value (Optional) The value for the lifetime of the security association. Must be a positive integer. Default is 3600.
- value_specs (Optional) Map of additional options.

- region See Argument Reference above.
- name See Argument Reference above.
- tenant_id See Argument Reference above.
- description See Argument Reference above.
- auth_algorithm See Argument Reference above.
- encapsulation_mode See Argument Reference above.
- encryption_algorithm See Argument Reference above.
- pfs See Argument Reference above.
- transform_protocol See Argument Reference above.
- lifetime See Argument Reference above.
 - unit See Argument Reference above.
 - value See Argument Reference above.
- value_specs See Argument Reference above.

Policies can be imported using the id, e.g.

\$ terraform import openstack_vpnaas_ipsec_policy_v2.policy_1 832cb7f3-59fe-40cf-8f64-8350ff6

» openstack_vpnaas_ike_policy_v2

Manages a V2 Neutron IKE policy resource within OpenStack.

» Example Usage

```
resource "openstack_vpnaas_ike_policy_v2" "policy_1" {
  name = "my_policy"
}
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VPN service. If omitted, the region argument of the provider is used. Changing this creates a new service.
- name (Optional) The name of the policy. Changing this updates the name of the existing policy.
- tenant_id (Optional) The owner of the policy. Required if admin wants to create a service for another policy. Changing this creates a new policy.
- description (Optional) The human-readable description for the policy. Changing this updates the description of the existing policy.
- auth_algorithm (Optional) The authentication hash algorithm. Valid values are sha1, sha256, sha384, sha512. Default is sha1. Changing this updates the algorithm of the existing policy.
- encryption_algorithm (Optional) The encryption algorithm. Valid values are 3des, aes-128, aes-192 and so on. The default value is aes-128. Changing this updates the existing policy.
- pfs (Optional) The perfect forward secrecy mode. Valid values are Group2, Group5 and Group14. Default is Group5. Changing this updates the existing policy.

- phase1_negotiation_mode (Optional) The IKE mode. A valid value is main, which is the default. Changing this updates the existing policy.
- ike_version (Optional) The IKE mode. A valid value is v1 or v2. Default is v1. Changing this updates the existing policy.
- lifetime (Optional) The lifetime of the security association. Consists of Unit and Value.
 - unit (Optional) The units for the lifetime of the security association.
 Can be either seconds or kilobytes. Default is seconds.
 - value (Optional) The value for the lifetime of the security association. Must be a positive integer. Default is 3600.
- value_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant_id See Argument Reference above.
- description See Argument Reference above.
- auth_algorithm See Argument Reference above.
- encapsulation_mode See Argument Reference above.
- encryption_algorithm See Argument Reference above.
- pfs See Argument Reference above.
- transform_protocol See Argument Reference above.
- lifetime See Argument Reference above.
 - unit See Argument Reference above.
 - value See Argument Reference above.
- value_specs See Argument Reference above.

» Import

Services can be imported using the id, e.g.

\$ terraform import openstack_vpnaas_ike_policy_v2.policy_1 832cb7f3-59fe-40cf-8f64-8350ffc03

» openstack_vpnaas_service_v2

Manages a V2 Neutron VPN service resource within OpenStack.

» Example Usage

```
resource "openstack_vpnaas_service_v2" "service_1" {
  name = "my_service"
  router_id = "14a75700-fc03-4602-9294-26ee44f366b3"
  admin_state_up = "true"
}
```

» Argument Reference

The following arguments are supported:

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create a VPN service. If omitted, the region argument of the provider is used. Changing this creates a new service.
- name (Optional) The name of the service. Changing this updates the name of the existing service.
- tenant_id (Optional) The owner of the service. Required if admin wants to create a service for another project. Changing this creates a new service.
- description (Optional) The human-readable description for the service. Changing this updates the description of the existing service.
- admin_state_up (Optional) The administrative state of the resource. Can either be up(true) or down(false). Changing this updates the administrative state of the existing service.
- subnet_id (Optional) SubnetID is the ID of the subnet. Default is null.
- router_id (Required) The ID of the router. Changing this creates a new service.
- value_specs (Optional) Map of additional options.

» Attributes Reference

- region See Argument Reference above.
- name See Argument Reference above.
- tenant_id See Argument Reference above.
- router id See Argument Reference above.
- admin_state_up See Argument Reference above.
- subnet_id See Argument Reference above.

- status Indicates whether IPsec VPN service is currently operational. Values are ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING UPDATE, or PENDING DELETE.
- external_v6_ip The read-only external (public) IPv6 address that is used for the VPN service.
- external_v4_ip The read-only external (public) IPv4 address that is used for the VPN service.
- description See Argument Reference above.
- value_specs See Argument Reference above.

Services can be imported using the id, e.g.

\$ terraform import openstack_vpnaas_service_v2.service_1 832cb7f3-59fe-40cf-8f64-8350ffc032

» openstack_vpnaas_endpoint_group_v2

Manages a V2 Neutron Endpoint Group resource within OpenStack.

» Example Usage

» Argument Reference

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an endpoint group. If omitted, the region argument of the provider is used. Changing this creates a new group.
- name (Optional) The name of the group. Changing this updates the name of the existing group.
- tenant_id (Optional) The owner of the group. Required if admin wants to create an endpoint group for another project. Changing this creates a new group.

- description (Optional) The human-readable description for the group. Changing this updates the description of the existing group.
- type The type of the endpoints in the group. A valid value is subnet, cidr, network, router, or vlan. Changing this creates a new group.
- endpoints List of endpoints of the same type, for the endpoint group. The values will depend on the type. Changing this creates a new group.
- value_specs (Optional) Map of additional options.

The following attributes are exported:

- region See Argument Reference above.
- name See Argument Reference above.
- tenant_id See Argument Reference above.
- description See Argument Reference above.
- type See Argument Reference above.
- endpoints See Argument Reference above.
- value_specs See Argument Reference above.

» Import

Groups can be imported using the id, e.g.

\$ terraform import openstack_vpnaas_endpoint_group_v2.group_1 832cb7f3-59fe-40cf-8f64-8350f:

» openstack vpnaas site connection v2

Manages a V2 Neutron IPSec site connection resource within OpenStack.

» Example Usage

```
resource "openstack_vpnaas_site_connection_v2" "conn_1" {
    name = "connection_1"
    ikepolicy_id = "${openstack_vpnaas_ike_policy_v2.policy_2.id}"
    ipsecpolicy_id = "${openstack_vpnaas_ipsec_policy_v2.policy_1.id}"
    vpnservice_id = "${openstack_vpnaas_service_v2.service_1.id}"
    psk = "secret"
    peer_address = "192.168.10.1"
    local_ep_group_id = "${openstack_vpnaas_endpoint_group_v2.group_2.id}"
    peer_ep_group_id = "${openstack_vpnaas_endpoint_group_v2.group_1.id}"
```

- region (Optional) The region in which to obtain the V2 Networking client. A Networking client is needed to create an IPSec site connection. If omitted, the region argument of the provider is used. Changing this creates a new site connection.
- name (Optional) The name of the connection. Changing this updates the name of the existing connection.
- tenant_id (Optional) The owner of the connection. Required if admin wants to create a connection for another project. Changing this creates a new connection.
- description (Optional) The human-readable description for the connection. Changing this updates the description of the existing connection.
- admin_state_up (Optional) The administrative state of the resource. Can either be up(true) or down(false). Changing this updates the administrative state of the existing connection.
- ikepolicy_id (Required) The ID of the IKE policy. Changing this creates a new connection.
- vpnservice_id (Required) The ID of the VPN service. Changing this
 creates a new connection.
- local_ep_group_id (Optional) The ID for the endpoint group that contains private subnets for the local side of the connection. You must specify this parameter with the peer_ep_group_id parameter unless in backward-compatible mode where peer_cidrs is provided with a subnet_id for the VPN service. Changing this updates the existing connection.
- ipsecpolicy_id (Required) The ID of the IPsec policy. Changing this creates a new connection.
- peer_id (Required) The peer router identity for authentication. A valid value is an IPv4 address, IPv6 address, e-mail address, key ID, or FQDN. Typically, this value matches the peer_address value. Changing this updates the existing policy.
- peer_ep_group_id (Optional) The ID for the endpoint group that contains private CIDRs in the form < net_address > / < prefix > for the peer side of the connection. You must specify this parameter with the local_ep_group_id parameter unless in backward-compatible mode where peer cidrs is provided with a subnet id for the VPN service.

- local_id (Optional) An ID to be used instead of the external IP address for a virtual router used in traffic between instances on different networks in east-west traffic. Most often, local ID would be domain name, email address, etc. If this is not configured then the external IP address will be used as the ID.
- peer_address (Required) The peer gateway public IPv4 or IPv6 address or FQDN.
- psk (Required) The pre-shared key. A valid value is any string.
- initiator (Optional) A valid value is response-only or bi-directional.
 Default is bi-directional.
- peer_cidrs (Optional) Unique list of valid peer private CIDRs in the form < net_address > / < prefix > .
- dpd (Optional) A dictionary with dead peer detection (DPD) protocol controls.
 - action (Optional) The dead peer detection (DPD) action. A valid value is clear, hold, restart, disabled, or restart-by-peer. Default value is hold.
 - timeout (Optional) The dead peer detection (DPD) timeout in seconds. A valid value is a positive integer that is greater than the DPD interval value. Default is 120.
 - interval (Optional) The dead peer detection (DPD) interval, in seconds. A valid value is a positive integer. Default is 30.
- mtu (Optional) The maximum transmission unit (MTU) value to address fragmentation. Minimum value is 68 for IPv4, and 1280 for IPv6.
- value_specs (Optional) Map of additional options.

- region See Argument Reference above.
- name See Argument Reference above.
- tenant_id See Argument Reference above.
- admin_state_up See Argument Reference above.
- description See Argument Reference above.
- dpd See Argument Reference above.
- psk See Argument Reference above.
- initiator See Argument Reference above.
- peer_address See Argument Reference above.
- peer id See Argument Reference above.
- peer cidrs See Argument Reference above.

- mtu See Argument Reference above.
- local_id See Argument Reference above.
- peer_ep_group_id See Argument Reference above.
- ipsecpolicy_id See Argument Reference above.
- vpnservice_id See Argument Reference above.
- ikepolicy_id See Argument Reference above.
- value_specs See Argument Reference above.

Site Connections can be imported using the id, e.g.

\$ terraform import openstack_vpnaas_site_connection_v2.conn_1 832cb7f3-59fe-40cf-8f64-8350f

» sharedfilesystem_securityservice_v2

Use this resource to configure a security service.

A security service stores configuration information for clients for authentication and authorization (AuthN/AuthZ). For example, a share server will be the client for an existing service such as LDAP, Kerberos, or Microsoft Active Directory.

Minimum supported Manila microversion is 2.7.

» Example Usage

```
resource "openstack_sharedfilesystem_securityservice_v2" "securityservice_1" {
             = "security"
 name
  description = "created by terraform"
            = "active_directory"
  type
             = "192.168.199.10"
 server
 dns_ip
             = "192.168.199.10"
             = "example.com"
 domain
             = "CN=Computers,DC=example,DC=com"
  011
             = "joinDomainUser"
  user
             = "s8cret"
  password
```

» Argument Reference

- region (Optional) The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to create a security service. If omitted, the region argument of the provider is used. Changing this creates a new security service.
- name (Optional) The name of the security service. Changing this updates the name of the existing security service.
- description (Optional) The human-readable description for the security service. Changing this updates the description of the existing security service.
- type (Required) The security service type can either be active_directory, kerberos or ldap. Changing this updates the existing security service.
- dns_ip (Optional) The security service DNS IP address that is used inside the tenant network.
- ou (Optional) The security service ou. An organizational unit can be added to specify where the share ends up. New in Manila microversion 2.44.
- user (Optional) The security service user or group name that is used by the tenant.
- password (Optional) The user password, if you specify a user.
- domain (Optional) The security service domain.
- server (Optional) The security service host name or IP address.

- id The unique ID for the Security Service.
- region See Argument Reference above.
- project_id The owner of the Security Service.
- name See Argument Reference above.
- description See Argument Reference above.
- type See Argument Reference above.
- dns_ip See Argument Reference above.
- ou See Argument Reference above.
- user See Argument Reference above.
- password See Argument Reference above.
- domain See Argument Reference above.
- server See Argument Reference above.

This resource can be imported by specifying the ID of the security service:

\$ terraform import openstack_sharedfilesystem_securityservice_v2.securityservice_1 <id>

» sharedfilesystem_sharenetwork_v2

Use this resource to configure a share network.

A share network stores network information that share servers can use when shares are created.

» Example Usage

» Basic share network

```
resource "openstack_networking_network_v2" "network_1" {
                 = "network 1"
  admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
 name = "subnet 1"
 cidr = "192.168.199.0/24"
 ip\_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
 name
                     = "test_sharenetwork"
 description = "test share network"
neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
» Share network with associated security services
resource "openstack_networking_network_v2" "network_1" {
                 = "network 1"
  admin_state_up = "true"
}
```

```
resource "openstack_networking_subnet_v2" "subnet_1" {
 name = "subnet_1"
  cidr = "192.168.199.0/24"
  ip\_version = 4
  network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_sharedfilesystem_securityservice_v2" "securityservice_1" {
             = "security"
  description = "created by terraform"
           = "active_directory"
  type
             = "192.168.199.10"
  server
 dns_ip
             = "192.168.199.10"
             = "example.com"
  domain
  011
             = "CN=Computers, DC=example, DC=com"
             = "joinDomainUser"
  user
             = "s8cret"
  password
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
                     = "test_sharenetwork"
  description
                     = "test share network with security services"
 neutron_net_id
                     = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
  security_service_ids = [
    "${openstack sharedfilesystem securityservice v2.securityservice 1.id}",
}
```

- region (Optional) The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to create a share network. If omitted, the region argument of the provider is used. Changing this creates a new share network.
- name (Optional) The name for the share network. Changing this updates the name of the existing share network.
- description (Optional) The human-readable description for the share network. Changing this updates the description of the existing share network.
- neutron_net_id (Required) The UUID of a neutron network when setting up or updating a share network. Changing this updates the existing

share network if it's not used by shares.

- neutron_subnet_id (Required) The UUID of the neutron subnet when setting up or updating a share network. Changing this updates the existing share network if it's not used by shares.
- security_service_ids (Optional) The list of security service IDs to associate with the share network. The security service must be specified by ID and not name.

» Attributes Reference

- id The unique ID for the Share Network.
- region See Argument Reference above.
- project_id The owner of the Share Network.
- name See Argument Reference above.
- description See Argument Reference above.
- neutron_net_id See Argument Reference above.
- neutron_subnet_id See Argument Reference above.
- security_service_ids See Argument Reference above.
- network_type The share network type. Can either be VLAN, VXLAN, GRE, or flat.
- segmentation_id The share network segmentation ID.
- cidr The share network CIDR.
- ip_version The IP version of the share network. Can either be 4 or 6.

» Import

This resource can be imported by specifying the ID of the share network:

\$ terraform import openstack_sharedfilesystem_sharenetwork_v2.sharenetwork_1 <id>

$\begin{tabular}{ll} \verb|w| openstack_shared filesystem_share_v2 \\ \end{tabular}$

Use this resource to configure a share.

» Example Usage

```
resource "openstack_networking_subnet_v2" "subnet_1" {
 name = "subnet_1"
 cidr = "192.168.199.0/24"
 ip\_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
                     = "test sharenetwork"
 description
                    = "test share network with security services"
 neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_sharedfilesystem_share_v2" "share_1" {
                 = "nfs share"
 description
                = "test share description"
                 = "NFS"
 share_proto
                  = 1
 size
  share_network_id = "${openstack_sharedfilesystem_sharenetwork_v2.sharenetwork_1.id}"
}
```

- region The region in which to obtain the V2 Shared File System client.
 A Shared File System client is needed to create a share. Changing this creates a new share.
- name (Optional) The name of the share. Changing this updates the name of the existing share.
- description (Optional) The human-readable description for the share. Changing this updates the description of the existing share.
- share_proto (Required) The share protocol can either be NFS, CIFS, CEPHFS, GLUSTERFS, HDFS or MAPRFS. Changing this creates a new share.
- size (Required) The share size, in GBs. The requested share size cannot be greater than the allowed GB quota. Changing this resizes the existing share.
- share_type (Optional) The share type name. If you omit this parameter, the default share type is used.

- snapshot_id (Optional) The UUID of the share's base snapshot. Changing this creates a new share.
- is_public (Optional) The level of visibility for the share. Set to true to make share public. Set to false to make it private. Default value is false. Changing this updates the existing share.
- metadata (Optional) One or more metadata key and value pairs as a dictionary of strings.
- share_network_id (Optional) The UUID of a share network where the share server exists or will be created. If share_network_id is not set and you provide a snapshot_id, the share_network_id value from the snapshot is used. Changing this creates a new share.
- availability_zone (Optional) The share availability zone. Changing this creates a new share.

- id The unique ID for the Share.
- region See Argument Reference above.
- project_id The owner of the Share.
- name See Argument Reference above.
- description See Argument Reference above.
- share_proto See Argument Reference above.
- size See Argument Reference above.
- share_type See Argument Reference above.
- snapshot id See Argument Reference above.
- is public See Argument Reference above.
- metadata See Argument Reference above.
- share_network_id See Argument Reference above.
- availability_zone See Argument Reference above.
- export_locations A list of export locations. For example, when a share server has more than one network interface, it can have multiple export locations.
- has_replicas Indicates whether a share has replicas or not.
- host The share host name.
- replication_type The share replication type.
- share_server_id The UUID of the share server.

» Import

This resource can be imported by specifying the ID of the share:

\$ terraform import openstack_sharedfilesystem_share_v2.share_1 <id>

» openstack_sharedfilesystem_share_access_v2

Use this resource to control the share access lists.

» Example Usage

» NFS

```
resource "openstack_networking_network_v2" "network_1" {
               = "network 1"
 admin_state_up = "true"
}
resource "openstack_networking_subnet_v2" "subnet_1" {
 name = "subnet_1"
 cidr = "192.168.199.0/24"
 ip\_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
}
resource "openstack_sharedfilesystem_share_v2" "share_1" {
                = "nfs_share"
 description = "test share description"
share_proto = "NFS"
 share_network_id = "${openstack_sharedfilesystem_sharenetwork_v2.sharenetwork_1.id}"
resource "openstack_sharedfilesystem_share_access_v2" "share_access_1" {
           = "${openstack_sharedfilesystem_share_v2.share_1.id}"
 access_type = "ip"
           = "192.168.199.10"
 access to
 access level = "rw"
}
```

» CIFS

```
resource "openstack_networking_network_v2" "network_1" {
                = "network 1"
  admin_state_up = "true"
}
resource "openstack networking subnet v2" "subnet 1" {
 name = "subnet 1"
  cidr = "192.168.199.0/24"
  ip\_version = 4
 network_id = "${openstack_networking_network_v2.network_1.id}"
}
resource "openstack_sharedfilesystem_securityservice_v2" "securityservice_1" {
             = "security"
  description = "created by terraform"
           = "active_directory"
  type
             = "192.168.199.10"
  server
 dns_ip
             = "192.168.199.10"
             = "example.com"
 domain
             = "CN=Computers, DC=example, DC=com"
  ou
            = "joinDomainUser"
 user
 password = "s8cret"
resource "openstack_sharedfilesystem_sharenetwork_v2" "sharenetwork_1" {
                     = "test_sharenetwork_secure"
                    = "share the secure love"
  description
 neutron_net_id = "${openstack_networking_network_v2.network_1.id}"
 neutron_subnet_id = "${openstack_networking_subnet_v2.subnet_1.id}"
  security_service_ids = [
    "${openstack_sharedfilesystem_securityservice_v2.securityservice_1.id}",
 ]
}
resource "openstack_sharedfilesystem_share_v2" "share_1" {
                  = "cifs share"
 name
  share_proto
                  = "CIFS"
                  = 1
 size
  share_network_id = "${openstack_sharedfilesystem_sharenetwork_v2.sharenetwork_1.id}"
}
resource "openstack_sharedfilesystem_share_access_v2" "share_access_1" {
  share_id = "${openstack_sharedfilesystem_share_v2.share_1.id}"
```

```
access_type = "user"
access_to = "windows"
access_level = "ro"
}

resource "openstack_sharedfilesystem_share_access_v2" "share_access_2" {
    share_id = "${openstack_sharedfilesystem_share_v2.share_1.id}"
    access_type = "user"
    access_to = "linux"
    access_level = "rw"
}

output "export_locations" {
    value = "${openstack_sharedfilesystem_share_v2.share_1.export_locations}"
}
```

The following arguments are supported:

- region The region in which to obtain the V2 Shared File System client. A Shared File System client is needed to create a share access. Changing this creates a new share access.
- share_id (Required) The UUID of the share to which you are granted access.
- access_type (Required) The access rule type. Can either be an ip, user or cert.
- access_to (Required) The value that defines the access. Can either be
 an IP address or a username verified by configured Security Service of the
 Share Network.
- access_level (Required) The access level to the share. Can either be rw or ro.

» Attributes Reference

- id The unique ID for the Share Access.
- region See Argument Reference above.
- share_id See Argument Reference above.
- access_type See Argument Reference above.
- access_to See Argument Reference above.
- access_level See Argument Reference above.

This resource can be imported by specifying the ID of the share and the ID of the share access, separated by a slash, e.g.:

\$ terraform import openstack_sharedfilesystem_share_access_v2.share_access_1 <share id>/<share</pre>