tmux cheat sheet

(C-x means ctrl+x, M-x means alt+x)

1.1. Prefix key

The default prefix is C-b. If you (or your muscle memory) prefer C-a, you need to add this to ~/.tmux.conf:

```
# remap prefix to Control + a
set -g prefix C-a
# bind 'C-a C-a' to type 'C-a'
bind C-a send-prefix
unbind C-b
```

I'm going to assume that C-a is your prefix.

1.2. Sessions, windows, panes

Session is a set of windows, plus a notion of which window is current.

Window is a single screen covered with panes. (Once might compare it to a 'virtual desktop' or a 'space'.)

Pane is a rectangular part of a window that runs a specific command, e.g. a shell.

1.3. Getting help

Display a list of keyboard shortcuts:

C-a ?

Navigate using Vim or Emacs shortcuts, depending on the value of mode-keys. Emacs is the default, and if you want Vim shortcuts for help and copy modes (e.g. j, k, C-u, C-d), add the following line to ~/.tmux.conf:

```
setw -g mode-keys vi
```

Any command mentioned in this list can be executed as tmux something or C-a :something (or added to ~/.tmux.conf).

1.4. Managing sessions

Creating a session:

```
tmux new-session -s work
```

Create a new session that shares all windows with an existing session, but has its own separate notion of which window is current:

```
tmux new-session -s work2 -t work
```

Attach to a session:

 ${\tt tmux}$ attach ${\tt -t}$ work

Detach from a session: C-a d.

Switch between sessions:

C-a (previous session

C-a) next session

C-a L 'last' (previously used) session

C-a s choose a session from a list

Other:

C-a \$ rename the current session

C-a

1.5. Managing windows

Create a window:

```
C-a c create a new window
```

Switch between windows:

```
C-a 1 ... switch to window 1, ..., 9, 0 C-a 9
```

```
1.2.
```

C-a 0
C-a p previous window
C-a n next window
C-a 1 'last' (previously used) window
C-a w choose window from a list
Switch between windows with a twist:

 ${\tt C-a\ M-n}$ next window with a bell, activity or

content alert

C-a M-p previous such window

Other:

C-a , rename the current window
C-a & kill the current window

1.6. Managing split panes

Creating a new pane by splitting an existing one:

```
C-a " split vertically (top/bottom)
C-a % split horizontally (left/right)
```

Switching between panes:

```
C-a left go to the next pane on the left
C-a right (or one of these other directions)
C-a up
C-a down
```

C-a o go to the next pane (cycle through all of them)
C-a; go to the 'last' (previously used) pane

Moving panes around:

```
C-a { move the current pane to the previous position
C-a } move the current pane to the next position
C-a C-o rotate window 'up' (i.e. move all panes)
C-a M-o rotate window 'down'
C-a ! move the current pane into a new separate
    window ('break pane')
C-a :move-pane -t :3.2
    split window 3's pane 2 and move the current pane there
```

Resizing panes:

```
C-a M-up, C-a M-down, C-a M-left, C-a M-right
resize by 5 rows/columns
C-a C-up, C-a C-down, C-a C-left, C-a C-right
resize by 1 row/column
```

Applying predefined layouts:

```
C-a M-1 switch to even-horizontal layout
C-a M-2 switch to even-vertical layout
C-a M-3 switch to main-horizontal layout
C-a M-4 switch to main-vertical layout
C-a M-5 switch to tiled layout
C-a space switch to the next layout
```

Other:

C-a x kill the current pane

C-a q display pane numbers for a short while

1.7. Other config file settings

Force a reload of the config file on C-a r:

```
unbind r
bind r source-file ~/.tmux.conf
```

Some other settings that I use:

```
setw -g xterm-keys on
```