

VERDI 2.1 User Manual

03/30/2021

Contents

1	Introduction	6
1.1	Background	6
1.2	Where to Obtain VERDI	7
1.3	Where to Obtain VERDI Documentation	8
1.4	Help Desk Support for VERDI	13
1.5	Future VERDI Development	13
2	Requirements for Using VERDI	13
2.1	Java	13
2.2	Memory and CPU Requirements	13
2.3	Requirements to Run VERDI Remotely	14
2.4	Graphics Requirements	14
2.5	Display Properties	14
3	VERDI Installation Instructions	14
3.1	Installation Instructions for Linux and Mac	15
3.2	Installation Instructions for Windows	15
4	Starting VERDI and Getting Your Data into VERDI	17
4.1	Starting VERDI	17
4.1.1	Windows	17
4.1.2	Linux and Other Non-Windows JRE 7 Supported System Configurations	19
4.2	Main Window	19
4.3	Rearrange the Datasets, Formulas, and Areas Panes	21

5 Navigating VERDI's Main Menu Options	21
5.1 File Menu Options	22
5.1.1 Open Project	22
5.1.2 Save Project	22
5.1.3 View Script Editor	22
5.2 Plots Menu Options	22
5.2.1 Undock All Plots	23
5.2.2 Animate Tile Plots	23
5.3 Window Menu Options	24
5.3.1 Datasets, Areas, and Formulas	25
5.3.2 Script Editor	25
5.3.3 List of Plots	25
5.4 Help Menu Options	25
6 Working with Gridded Datasets	25
6.1 Gridded Input File Formats	25
6.1.1 Model File Format Conventions	25
6.1.2 Observational Data Formats	26
6.2 Example Datasets	27
6.3 Adding and Removing a Dataset from a Local File System	27
6.4 Adding and Removing a Dataset from a Remote File System	30
6.4.1 Remote File Browser	30
6.4.2 Adding Additional Remote Hosts	33
6.5 Variables List	33
6.6 Time Steps and Layers Panels	35
6.7 Saving Projects	35
7 Working with Formulas	35
7.1 Adding and Removing a Formula	37
7.2 Example Formulas	37
7.3 Selecting a Formula for Plotting	37
7.4 Saving Formulas	39
7.5 Time Step and Layer Ranges	39

8 Working with Area Files	39
8.1 Area File Formats	39
8.2 Example Area File	39
8.3 Requirements for Shapefiles used in Areal Interpolation	40
8.4 Adding and Removing an Area File	40
8.5 Areas List	40
8.6 Areal Interpolation	40
9 ‘Subsetting Spatial and Temporal Data	40
9.1 Specify Time Step Range	45
9.2 Specify Layer Range	45
9.3 Specify Domain Range	46
9.4 Rules of Precedence for Subsetting Data	46
10 Creating Plots	47
10.1 Tile Plot	47
10.1.1 Time Selection and Animation Controls	47
10.1.2 Layer Selection	49
10.1.3 Grid Cell Time Aggregate Statistics	49
10.2 Areal Interpolation Plot	50
10.2.1 Options Menu	50
10.2.2 Areal Values for Polygon Segment	50
10.2.3 View and Export Areal Interpolation Plot Data in Text Format	56
10.2.4 Export Areal Interpolation Plot Data to Shapefiles	56
10.3 Vertical Cross Section Plot	56
10.4 Time Series Plot	56
10.5 Time Series Bar Plot	65
10.6 Scatter Plot	65
10.7 Contour Plot	66

11 Plot Menu Bar	67
11.1 File Menu	67
11.2 Configure Menu	71
11.2.1 Configure Plot	71
11.2.2 Save Configuration	75
11.2.3 Load Configuration	79
11.2.4 Load Chart Theme	79
11.2.5 Edit Chart Theme	79
11.2.6 Save Chart Theme	83
11.3 Controls Menu	83
11.3.1 Zoom	83
11.3.2 Probe	86
11.3.3 Set Row and Column Ranges	87
11.3.4 Show Grid Lines	89
11.3.5 Show Latitude and Longitude	89
11.4 Plot Menu Options	89
11.4.1 Time Series Plots	89
11.4.2 Animate Plots	89
11.4.3 Add Overlays	92
11.5 GIS Layers	98
11.5.1 Add Map Layers	98
11.5.2 Configure GIS Layers	99
12 Supported Grid and Coordinate Systems (Map Projections)	99
12.1 Models-3 I/O API Data Convention	99
12.2 CAMx Gridded Data Convention	100
12.3 WRF netCDF Data Convention	106
12.4 MPAS netCDF Data Convention	106
13 Models-3 I/O API Utilities, Data Conversion Programs, and Libraries	106
14 Contributing to VERDI Development	110
15 Known Bugs	110

16 Mathematical Functions	110
16.1 Unary Functions	111
16.2 Binary Operators	112
16.3 Boolean Operators	113
16.4 Time Step Index	113
17 VERDI Batch Script Editor	114
18 Command Line Scripting	114
18.1 Example Command Line Script for Linux Users	114
18.2 Example Command Line Script for Windows Users	115
19 Areal Interpolation Calculations	120
20 Licenses for JAVA Libraries used by VERDI	121
21 Acknowledgments	122
21.1 Data Contributions	122
21.2 Data Reader Contributions	122

Visualization Environment for Rich Data Interpretation (VERDI): User's Manual

U.S. EPA Contract No. EP-W-09-023, "Operation of the Center for Community Air Quality Modeling and Analysis (CMAS)" Prepared for: Donna Schwede U.S. EPA, ORD/NERL/AMD/APMB E243-04 USEPA Mailroom Research Triangle Park, NC 27711 Prepared by: Liz Adams (UNC-IE) and Yongping Yuan (USEPA) Date: March 30, 2021

1 Introduction

1.1 Background

This manual describes how to use the Visualization Environment for Rich Data Interpretation (VERDI). VERDI is a flexible and modular Java-based visualization software tool that allows users to visualize multivariate gridded environmental datasets created by environmental modeling systems such as the Community Multiscale Air Quality (CMAQ) modeling system, the Weather Research and Forecasting (WRF) modeling system, and Model for Prediction Across Scales (MPAS). These systems produce files of gridded concentration and deposition fields that users need to visualize and compare with observational data both spatially and temporally. VERDI can facilitate these types of analyses.

Initial development of VERDI was done by the Argonne National Laboratory for the U.S. Environmental Protection Agency (EPA) and its user community. Argonne National Laboratory's work was supported by the EPA through U.S. Department of Energy contract DE-AC02-06CH11357. Further development has been performed by the University of North Carolina Institute for the Environment under U.S. EPA Contract No. EP-W-05-045 and EP-W-09-023, by Lockheed Corporation under U.S. EPA contract No. 68-W-04-005, and Argonne National Laboratory. VERDI is licensed under the GNU General Public License (GPL) version 3, and the source code is available through verdi.sourceforge.net. Instructions for developers within the community are included in the VERDI Developer Instructions (see Section 1.3). VERDI is supported by the Community Modeling and Analysis System (CMAS) Center under U.S. EPA Contract No. EP-W-09-023. The batch script and VERDI Script Editor were developed and documented under U.S. EPA Contract No. EP-D-07-102, through an Office of Air Quality Planning and Standards project managed by Kirk Baker. The CMAS Center is located within the Institute for the Environment at the University of North Carolina at Chapel Hill.

This manual describes VERDI version 2.1 released in March 2021.

The following are useful web links for obtaining VERDI downloads and support:

1. VERDI Visualization Tool web site:

<http://www.cmascenter.org/verdi>

1. CMAS download page for users of VERDI (requires a CMAS account):

https://www.cmascenter.org/download/forms/step_2.cfm?prod=11

1. CMAS GitHub website for developers of VERDI:

<https://github.com/CEMPD/VERDI>

1. VERDI Frequently Asked Questions (FAQs):

<https://www.cmascenter.org/help/faq.cfm>

Use pulldown menu to select VERDI product to view its FAQs.

1. To query and ask questions use the new CMAS User Forum, by selecting the VERDI category:
<https://forum.cmascenter.org/c/verdi>

2. To query the older M3USER listserv for VERDI related technical support questions and answers:
<http://lists.unc.edu/read/?forum=m3user>

3. To query bugs and submit bug reports, questions, and/or requests:

<https://github.com/CEMPD/VERDI/issues>

1.2 Where to Obtain VERDI

You can download the latest version of VERDI from <https://www.cmascenter.org/verdi/> (PDF see (Fig-1) and (2)) (Github see: [Figure1-1](#) and [Figure 1-2](#)). When you click on DOWNLOAD to download VERDI, you will be sent to the CMAS Model Download Center. To download and install VERDI, follow the instructions below, beginning at step 4. Alternatively, you may also begin at the CMAS web site <https://www.cmascenter.org>, and follow the instructions below:

1. Log in using an existing CMAS account, or create a new CMAS account.
2. Click the Download drop-down list and choose SOFTWARE.
3. From the Software Download, Step 1 page go to the box Select Software to Download on the right side of the page. Use the drop-down list to select VERDI, and then click Submit.
4. Select the product you wish to download, as shown in [Figure 3](#) (Fig1- 3)). Also specify the type of computer on which you will run VERDI (i.e., Linux PC, Windows, or Other) from the items in the scroll list. Note that the compilers question is not relevant for VERDI so please select Not Applicable. Finally, click Submit.
5. As shown in [Figure 4](#) (Fig1- 4)) follow the links to the appropriate version of the Linux, Mac, or Windows installation files. Links are also available for the current version of the documentation.




Figure 1: Top of VERDI Page

1.3 Where to Obtain VERDI Documentation

Documentation is available in several locations, described below. Each location provides links to the available documentation for VERDI, which can be viewed in your web browser or downloaded and saved to your computer.

- The main VERDI page has a link to Documentation.
- The VERDI download page on the CMAS website contains links to all of the available documentation.
- On the left-hand side of the www.cmascenter.org web site, open the drop-down menu for Help and choose Documentation. Select the documentation for VERDI from the drop-down list and click Search. Select the model release from the drop-down list and click Search. The resulting documentation pane shows that the available documentation for the chosen release of VERDI GitHub:[Figure 5](#) or PDF:[Fig- 5](#).
- To go directly to the most recent VERDI documentation click on DOCUMENTATION from the VERDI software: <http://www.cmascenter.org/verdi>. [Figure 6](#) shows the list of documentation that is available for download for VERDI 2.1.

model output, VERDI offers a range of options for viewing atmospheric modeling data. VERDI scripting provides a powerful interface for automating the production of graphics for analyzing your data.

Features:

Java

VERDI uses Java, which makes it easy to install and is portable across different operating systems.

VERDI packages are distributed for 64-bit Windows, Linux, and Mac.

GUI

The VERDI user environment is an intuitive GUI that makes importing datasets, creating formulas, and generating and saving plots easy.

Supported Plot Types

VERDI currently can be used to create 2-D tile plots, vertical cross sections, scatter plots, timeseries line, timeseries bar, 3-D contour plots, vector-tile plots, areal interpolation plots, and observation-tile plots.

Supported File Format Conventions

CMAQ Input/Output Applications Programming Interface (I/O API) netCDF, WRF netCDF, MPAS netCDF, CAMx (UAM-IV), and I/O API and text-based ASCII formats (for observational data).

Scriptable

VERDI can be driven with a scripting language to allow batch-generation of images.

Updates:

- Support for MPAS netCDF files.
- Updated world map.
- Option to display elevation for vertical cross-section plots.
- Can specify pixel size of exported raster (e.g., PNG) images.
- New statistics: count, fourth maximum, and custom percentile.
- Preliminary support for MCIP v5.0+ netCDF files.

History of VERDI

Driven by the air quality modeling community's need for a replacement to PAVE, the U.S. EPA sponsored the development of VERDI. PAVE is a Unix-based software system written in C and Motif. While the EPA is satisfied with the functionality of PAVE and desired to keep those capabilities, they recognize that the PAVE technology is outdated and wanted an updated, more efficient, flexible, and modular visualization software system. Argonne National Laboratory initially developed VERDI to duplicate the functionality of PAVE in a Java program. VERDI development continues thanks to the efforts of the U.S. EPA's National Computer Center/Environmental Modeling and Visualization Laboratory and the Institute for the Environment at the University of North Carolina - Chapel Hill.

PAVE program. Because PAVE is no longer in active development and support is limited, VERDI offers the best option as a state-of-the-art visualization program.

VERDI Training

Support

- CMAS Help Desk
- CMAS Center Forum - VERDI Category

Previous Documentation

2.0_BETA	<input type="button" value="Submit"/>
----------	---------------------------------------

Online Resources

- A New Tool for Analyzing CMAQ Modeling Results: Visualization Environment for Rich Data Interpretation (VERDI) - presented by Donna Schwede at the 2007 CMAS Conference.
- Visualization Environment for Rich Data Interpretation - VERDI - poster presented by Jo Ellen Brandmeyer and Elizabeth Adams at the 2016 CMAS Conference.

System Requirements

O/S	Windows, Linux, Mac
Memory	1024 MB RAM
Software	All needed VERDI components are contained in the distribution package.

Partners

- Institute for the Environment
- CMAS Center
- U.S. EPA Atmospheric & Environmental Systems Modeling Division
- U.S. EPA Environmental Modeling and Visualization Laboratory

Community Modeling and Analysis System (CMAS)

[More About CMAS](#) [Contact Us](#) [CMAS Newsletter](#)

General inquiries about the CMAS Center and questions about the web site should be directed to cmas@unc.edu



Figure 2: Bottom of VERDI Download Page


The screenshot shows the CMAS web site's software download interface. At the top, there is a search bar with 'Search for...' and a 'Search' button. Below the search bar is a navigation menu with links for Help, Download, Software, Conference, Training, Resources, User Details, and Log Out. A breadcrumb trail at the bottom of the header indicates the current location: HOME / DOWNLOAD / FORMS / STEP 2. The main content area has a heading 'Software Download, Step 2'. It includes instructions: 'Please select a particular software from the list. You can also optionally provide information about your platform and compiler for our developers' database. Choosing a platform/compiler will not influence your model download options.' Below these instructions are three dropdown menus: 'Select the product you wish to download:' set to 'VERDI 2.0', 'What platform will this run on?' set to '--Please Make a Selection--', and 'What compiler will you use?' set to '--Please Make a Selection--'. A blue 'Submit' button is located below the dropdowns. The footer contains the CMAS logo, the UNC Institute for the Environment logo, and links for More About CMAS, Contact Us, and CMAS Newsletter.

Figure 3: Downloading VERDI from the CMAS Web Site, Step 2

The screenshot shows the CMAS web site's software download interface, specifically for the VERDI 2.0 software. The layout is identical to Figure 3, with a search bar, navigation menu, and breadcrumb trail. The main content area has a large heading 'VERDI 2.0'. Below it, a note says 'Installation instructions, documentation, and software for VERDI 2.0'. A bold note at the top of the table row says 'NOTE: Save the files that you download into a common directory.' The table lists the available software packages:

File type	Download link and file name	Release/Modified date
Documentation	View	09/30/2019
Download for Windows	VERDI_2.0_win64_20190930.zip	09/30/2019
Download for Linux	VERDI_2.0_linux64_20190930.tar.gz	09/30/2019
Download for Mac OSX	VERDI_2.0_mac_20190930.tar.gz	09/30/2019
Download Observation Overlay Data	Link to the Google Drive Folder	08/26/2019

Figure 4: Downloading VERDI from the CMAS Web Site, Step 3



VERDI

Visualize gridded netCDF data with this easy-to-use Java program.

VERDI is a Java program for visualizing meteorology, emissions, and air quality modeling data. With options for overlaying GIS Shapefiles and observational data onto model output, VERDI offers a range of options for viewing atmospheric modeling data. VERDI scripting provides a powerful interface for automating the production of graphics for analyzing your data.

Features:

Java

VERDI uses Java, which makes it easy to install and is portable across different operating systems.

VERDI packages are distributed for 64-bit Windows, Linux, and Mac.

PAVE or VERDI?
How do you know if you should use PAVE or VERDI?
VERDI was developed as a replacement for the PAVE program. Because PAVE is no longer in active development and support is limited, VERDI offers the best option as a state-of-the-art visualization program.

Latest Version: VERDI version 2.0

[DOWNLOAD](#) | [DOCUMENTATION](#)

VERDI Training

Support

- [CMAS Help Desk](#)
- [CMAS Center Forum - VERDI Category](#)

Previous Documentation

2.0_BETA

Figure 5: VERDI Documentation on the CMAS Web Site

The screenshot shows the CMAS web site's documentation page for VERDI 2.1. At the top, there is a header bar with a search bar, a "CMAS" logo featuring a globe and icons, and a navigation menu with links for Help, Download, Software, Conference, Training, Resources, User Details, and Log Out. Below the header, a breadcrumb trail shows "HOME / HELP / DOCUMENTATION". The main content area has a dark background with a yellow-to-red gradient map of the world. The title "Documentation" is displayed in large, bold, black font. Below it, a section titled "The following documents are available for VERDI 2.0:" lists four items: "DEVELOPER GUIDE", "KNOWN ISSUES", "RELEASE NOTES", and "USERS GUIDE". There is also a link to "Search for other Model Documentation?". Further down, a note about a "Porting Guide" is followed by a statement about the nature of model research and development. A link to the "Software Download" page is provided. The bottom of the page features the "Community Modeling and Analysis System (CMAS)" logo, links to "More About CMAS", "Contact Us", and "CMAS Newsletter", and a note about general inquiries. The footer includes the UNC Institute for the Environment logo.

Figure 6: VERDI Documentation on the CMAS Web Site

1.4 Help Desk Support for VERDI

You are encouraged to search the new CMAS User Forum, by selecting the VERDI category: <https://forum.cmascenter.org/c/verdi> or using the old [M3USER listserv](#) for VERDI-related technical support questions; report errors and/or requests for enhancement to the m3user forum. The m3user forum is supported by the community and also by CMAS to help users resolve issues and identify and fix bugs found in supported software products.

1.5 Future VERDI Development

As stated in Schwede et al. (2007),[1] “VERDI is intended to be a community-based visualization tool with strong user involvement.” The VERDI source code is available to the public under a GNU Public License (GPL) license at <https://github.com/CEMPD/VERDI>. This allows users who wish to make improvements to VERDI to download the software, and to develop enhancements and improvements that they believe may be useful to the modeling community. Examples could include user-developed readers for additional file formats and modules for additional plot types. Users may wish to contribute data analysis routines, such as adding the ability to do bilinear interpolation (smoothing), or to contribute other enhancements to the existing plot types. The direction of future development will depend on the resources and the needs of the modeling community. If you are interested in contributing code to VERDI, please review the information in Chapter 14, “Contributing to VERDI Development.”

2 Requirements for Using VERDI

2.1 Java

VERDI uses OpenJDK version “15.0.1.” The OpenJDKTM is provided as part of the VERDI release for 32- and 64-bit Linux and Windows. If your computer requires a different version, see Section 3.3.

2.2 Memory and CPU Requirements

VERDI’s memory and CPU requirements largely depend on the size of the datasets to be visualized. Small datasets can be visualized and manipulated using less than 1024 megabytes of RAM, while larger datasets may need considerably more. If you are using datasets that require either more or less than 1024 MB of memory, you can change the default maximum memory setting used by VERDI:

- On Windows, edit the run.bat file that you use to launch VERDI. Look for the line that starts “set JAVACMD=” and change the value for the “Xmx” argument from the default heap size of 1024M.
- On Linux or another Unix platform, you can edit verdi.sh and replace the 1024 in –Xmx1024M with a different value; for example, -Xmx2048M will allow VERDI to access up to 2048MB (or 2GB) of RAM.

Note that slower CPUs can quickly view and animate smaller datasets, whereas larger datasets require more time. As a user opens new Tile plots or other plot types, the memory requirements increase. As the user then closes the plots, the memory is released by VERDI.

2.3 Requirements to Run VERDI Remotely

VERDI may be used to run on a remote compute server and have the graphics display locally on your desktop machine (Unix workstation, Mac, or PC) using the Tile Plot. Your computer needs to be configured to run X-Windows. Typically, you will connect to the remote compute server using secure shell (SSH). If you are using an X-Server and wish to generate 3-D plots using OpenGL, you need to turn on OpenGL support within the X-Server.

2.4 Graphics Requirements

Three-dimensional contour plots require a graphics card with OpenGL or DirectX capability. By default VERDI uses OpenGL for 3D rendering. If you would like to use DirectX instead, add the line: j3d=Dj3d.rend=d3d to the verdi.ini file.

2.5 Display Properties

VERDI works best on screen displays that have been set to a high or perhaps the highest screen resolution (1440×900 for Mac, or 1920×1080 for Windows 10). Follow these general instructions to adjust your screen resolution on the following types of computers.

- Windows 10: Click on the Start button and select Control Panel. Select Display, then Adjust resolution. Use the drop-down boxes to select your type of display, screen resolution, etc. (it may already be set at the highest resolution by default)
- Mac: Go to Applications and double-click on System Preferences. Under Hardware select Displays and then Select 1440×900 .

3 VERDI Installation Instructions

This chapter provides instructions for installing VERDI 2.0 on a variety of computer platforms. The supporting libraries required by VERDI are included in the installation, along with a version of the OpenJDK for your convenience.

VERDI 2.1 is distributed as a zip or gzip file, as appropriate, for each of the following supported platforms:

- 64-bit Windows 10

- 64-bit Linux
- Mac

If you have a different computer system, select the distribution for a computer system as close to yours as possible and proceed with the installation. Although Java is considered a write-once, run-anywhere computer language, that is not necessarily true for graphical software. Therefore, an appropriate version of some graphics libraries is included in each of the above VERDI distributions.

3.1 Installation Instructions for Linux and Mac

Follow these instructions to install VERDI:

1. tar -xvf VERDI_2.1_<linux,mac>_.tar.gz into a location where you would like to install VERDI
2. The run script for Linux is: verdi_2.1/verdi.sh The run script for Mac is: verdi_2.1/verdi.command
3. Create a directory *verdi* under your home directory.
4. Create an empty text file, name it *verdi.alias* and save it in your *verdi* directory. When you look at the directory listing for this *verdi* directory, you should see the *verdi.alias* file with a length of 0.
5. Locate the file *config.properties.TEMPLATE* that is in your installation directory. Copy *config.properties.TEMPLATE* to your *verdi* directory and rename that file *config.properties* only.
6. Add the path to the verdi run script to your .cshrc or .bash_profile so that the verdi.sh script can be found from any directory
example .cshrc set path = (\$path /proj/ie/proj/CMAS/VERDI/VERDI_2.1)
7. Alternatively, use alias to point to full path to verdi.sh alias verdi.sh /proj/ie/proj/CMAS/VERDI/VERDI_2.1/verdi
VERDI should now run if you execute the verdi.sh executable script on linux, or executing the verdi.command script on mac.

3.2 Installation Instructions for Windows

To install VERDI for Windows, unzip the file to a local directory on your Windows 10 computer.
NOTE: You do not need to install VERDI under a Program Files directory or in the root directory on one of your hard disk drives. Therefore, you should not need Administrator rights to install VERDI 2.0. If your system is under strict control from your Administrator, you may be able to unzip the VERDI distribution under your home directory or your documents directory; however, you may have problems if there is a space in the path to your VERDI installation directory.

If you are unable to install VERDI on your computer, please check to see whether your user account is authorized to install software. You may need to request that a user with a computer administrator

account install VERDI, or provide you with an account that has permission to install software. For more information about user account types, click Start and select Control Panel and then click on the User Account icon.

After successfully installing VERDI you may need to perform the following tasks under your home directory.

1. Locate your home directory. Your home directory is typically under csh `C: //Users//yourloginid`. So, if your login id is *staff*, your home directory is probably `C: //Users//staff`.
2. Create a new directory *verdi* under your home directory (e.g., `C: //Users//staff//verdi`).
3. Create an empty text file, name it *verdi.alias* and save it in your *verdi* directory. When you look at the directory listing for this *verdi* directory, you should see the *verdi.alias* file with a length of 0.
4. A text file named *config.properties.TEMPLATE* was installed into your VERDI installation directory. Copy *config.properties.TEMPLATE* to your *verdi* directory and rename that file *config.properties* only.

Note that VERDI writes a log file (i.e., *verdi.log*) as-needed to your *verdi* directory. This log file should remain small. However, if you need technical support we may ask for your log file. It will be a text file named *verdi.log* located in this *verdi* directory.

Setting VERDI Preferences

VERDI is configured via the *config.properties* file that you copied to your home/*verdi* directory. Edit this file to specify default directories for saving files, for placing the location of configuration files, and for saving project files. Contents of *config.properties.TEMPLATE*:

```
# This file should be put in $USER_HOME/verdi/ subdirectory
# Please use double backslash for Windows platform or slash for UNIX-like platforms
# Please uncomment the following lines and modify them to suit your local settings
# Windows example settings format
# verdi.project.home=C:// Users\\yourusername\\VERDI_2.1\\project
# verdi.config.home=C:// Users\\yourusername\\VERDI_2.1\\config
# Linux example settings format

verdi.project.home=.../..../data/project
verdi.config.home=.../..../data/configs
verdi.user.home=.../..../data/model
verdi.dataset.home=.../..../data/model
verdi.script.home=.../..../data/scripts

# file folder used as default location of HUC datasets for areal interpolation

verdi.hucData=.../..../data/hucRegion/
```

```
# For VERDI to access remote big netCDF data files
```

```
verdi.remote.hosts=terrae.nesc.epa.gov,vortex.rtpnc.epa.gov,garnet01.rtpnc.epa.gov,tulip.rtpnc.  
remote.file.util=/usr/local/bin/RemoteFileUtility  
verdi.remote.ssh=/usr/bin/ssh
```

```
# on local machine where VERDI is running. Used to hold temporary data file downloaded from a remote machine
```

```
verdi.temporary.dir=C:\\\\ Users\\username\\temp
```

The items in the config.properties.TEMPLATE file that is installed with VERDI are commented out. To specify default directories, uncommented these lines by removing the starting ‘#’ sign. Example settings that are provided in the default file show how to specify the paths to these locations, depending on whether the installation is for a Windows or Linux platform. Here are how the settings are used by VERDI. Note that VERDI stores the most recently used directory for each of these functions and will go to that directory when you repeat the load or save in the same session.

- verdi.project.home: Default location from which to load and save projects
- verdi.config.home: Default location from which to load and save plot configuration files
- verdi.dataset.home: Default location from which to load datasets
- verdi.script.home: Default location from which to load and save batch scripts
- verdi.hucData: Default location where area shapefiles are located; VERDI navigates to this directory when the user selects to add a dataset in the Area pane.
- verdi.remote.hosts: Contains a list of machines that the user can select to browse when adding a remote dataset using VERDI’s Remote File Access capability
- verdi.remote.util: Location of the RemoteFileUtility script for Linux and Mac installations of VERDI.


Starting in VERDI version 1.4, the ui.properties file was removed and the user-configurable settings, such as the default directory locations, were moved to the config.properties file.

4 Starting VERDI and Getting Your Data into VERDI

4.1 Starting VERDI

4.1.1 Windows

If you have previously configured this VERDI installation, use Windows Explorer to navigate to your installation directory. Double-click on the file **run.bat** to start VERDI. Alternatively, you can open a command window. If you do not have a shortcut to launch a command window, press the Start button and type **cmd** in the *Search programs and files* textbox. If your window is too small, go to the



```

run.bat - Notepad
File Edit Format View Help
@ECHO OFF
SET BATCHFILE=%~f2
REM Instructions: If your USER_HOME directory is not already set,
REM you can set it here (set USER_HOME=C:\Users\myUserName).
REM Your VERDI log file will be written in the verdi subdirectory.
REM Refer to your VERDI User's Guide for more information.
SET USER_HOME=%USERPROFILE%
set VERDI_USER=c:\users\ellenjo

REM Set the following path to the location where you installed VERDI.
SET VERDI_HOME=C:\\VERDI\\VERDI_1.6alpha
REM Change the following path if you are not using the version of Java installed with VERDI
set JAVADIR=%VERDI_HOME%\\jre1.7.0

REM Do not edit below this line
REM *****
CD .\\plugins\\bootstrap
SET JAVA=%JAVADIR%\\bin\\java
set CLASSPATH=%JAVADIR%\\bin\\*;%JAVADIR%\\lib\\*;%VERDI_HOME%\\plugins\\bootstrap\\bootstrap.jar;%VERDI_HOME%\\plugins\\bootstrap\\lib\\*;%VERDI_HOME%\\plugins\\bootstrap\\lib\\saf.core.runtime.jar;%VERDI_HOME%\\plugins\\bootstrap\\lib\\*;%VERDI_HOME%\\plugins\\core\\lib\\*

REM set PATH based on 32/64 windows
set bit64=n
if /I %Processor_Architecture%==AMD64 set bit64=y
if /I "%PROCESSOR_ARCHITEW6432%"=="AMD64" set bit64=y

if /I %bit64%==y GOTO proc64
set PATH=%PATH%;%VERDI_HOME%\\plugins\\core\\lib\\win32
REM echo set to win32 path
GOTO proc32

:proc64
set PATH=%PATH%;%VERDI_HOME%\\plugins\\core\\lib\\win64
REM echo set to win64 path

:proc32
REM path has been reset for DLLs; continue
set JAVACMD=%JAVA% -Xmx1024M -classpath %CLASSPATH% saf.core.runtime.Boot

IF "%1" == "-b" GOTO scripting
IF "%1" == "-batch" GOTO scripting

%JAVACMD% %
GOTO end

:scripting
%JAVACMD% %1 %BATCHFILE%

:end
CD ..\\..\

```

Figure 7: Starting VERDI in Windows

window's title bar and right-click; select Properties and then Layout and change your Screen Buffer Size and your Window Size appropriately.

Next, navigate to where you installed VERDI on your computer. You see the **run.bat** file. Its contents are shown in PDF:(Fig- 7) or GitHub:[Figure 7](#). If you have previously executed this VERDI installation, just type **run** and press the **Enter** key. Otherwise, you may need to customize some of the settings in this file for your configuration. If so, edit your run.bat in a text editor such as Notepad.

VERDI_HOME needs to point to the directory where VERDI is installed, which is also the directory containing the run.bat file. In this figure VERDI is installed in the directory C:\\VERDI\\VERDI_2.1.

JAVADIR needs to point to the directory where your JRE7 is installed. In this figure JRE7 is installed in the jre1.7.0 directory under the VERDI_HOME directory. If you are using a JRE in a different location on your computer, change the path in your run.bat file.

All other locations are specified relative to the VERDI_HOME or the JAVADIR, so you should not need to change any of those.

4.1.2 Linux and Other Non-Windows JRE 7 Supported System Configurations

To start VERDI from Linux and other non-Windows JRE 7 Supported System Configurations, find the directory where VERDI was installed; then run the verdi.sh script. On a Mac go to the /Applications/verdi_2.1 directory and run the verdi.command script. If you have set up the path environment variable on your .cshrc or .bash_profile or set up an alias to specify the full path, then you can run VERDI from any directory.

4.2 Main Window

When VERDI starts it displays its title screen as it loads. The main window is then displayed PDF:(Figure 8) or Github:(Figure 8). The top of the main window contains a menu bar with the main window options (**File, Plots, Window, and Help**). Below the menu bar are three icons that are shortcuts to some of the options available in the Main Window Menu Bar; the first is an **Open Project** icon, the second is a **Save Project** icon, the third is an icon that allows you to **Undock All Plots**. These shortcuts and the options available in the Main Window Menu Bar are discussed further in Chapter 5, “Navigating VERDI’s Main Menu Options.”

To the right of these three shortcut icons are buttons that list all of the available plot types. The **Selected Formula** is displayed on the far right. The Selected Formula refers to the formula that has been selected in the **Formula** pane (discussed briefly below and in detail in Chapter 7) and that will be used to create plots.

Below the icons and plot buttons, the VERDI window is divided into two main areas: a parameters area consisting of tabbed panes on the left side and a plots area on the right side. You can resize the entire window with your mouse. You can also resize the tabbed pane separately from the plot area by placing your mouse over the dividing line between them and then moving it to the left or the right. If you want, you can separate the tabbed pane into 3 panes by using your mouse to hold onto the pane’s title bar and then move it slightly out of alignment. To reassemble the 3 panes into a tabbed pane, use your mouse to hold onto the title bar of one pane, drag it until its outline fills the outline of another pane, and then release the mouse.

The parameters area contains three tabbed panes:

- The **Datasets** pane is used to load in the dataset files that you want to work with in this session (see Chapter 6). Once the datasets are loaded, VERDI automatically displays the lists of variables that are in the datasets. To see the variables in a dataset, click on the dataset, and the variables will be displayed in the **Variables** panel underneath the list of datasets. Double-click on the name of a variable listed on the variables panel to add it as a formula on the **Formula** pane; it also will be displayed as Selected Formula in the top right corner of the main VERDI window and will be the default formula for new plots that are created.
- The **Formulas** pane is used to create a formula that refers to the variable and the dataset that you are interested in plotting (see Chapter 7). All plots in VERDI are generated from formulas. A formula can be as simple as a single variable from one dataset or it can be an equation that uses variables from one or more datasets.




Figure 8: VERDI Main Window

- Use the **Areas** pane to load area files for creating areal interpolation plots (see Chapter 8). An area file is defined as a shapefile that contains polygon features such as watersheds, counties, or any other set of closed polygons.

Any plots that are created are shown in the plots area on the right-hand side of the main window. These plots can be placed into their own movable windows using Plots>Undock all Plots on VERDI's main menu, as discussed in Section 5.2.1. The Tile Plot has an option (Plot>Add Overlay> Vectors) to create a Tile Plot of a variable with a vector overlay of wind vectors or other vector types. The Vector Plot has now been removed because the Tile Plot with vector overlay is superior. The functions that are currently enabled for Tile Plots are described in Section 10.1.

4.3 Rearrange the Datasets, Formulas, and Areas Panes

You can rearrange the **Datasets**, **Formulas**, and **Areas** panes to be most efficient for your current work. VERDI supports resizing the entire VERDI window, floating one or more panes to other locations on your desktop, and rearranging the panes within the VERDI window.

The **Datasets**, **Formulas**, and **Areas** panes can each be configured to float so you can position them elsewhere on your desktop. To allow a pane to float, click the icon at the top of the pane that looks like a rectangle with an angle bracket above the upper-right corner; its tool tip is “Externalize this view into a floating window.” You can then click on the pane and drag it independently of the VERDI main window. For example, this is useful when you are entering a formula in the **Formulas** pane and need to refer to the variables that are in a loaded dataset. Once a pane is disconnected from the frame, the icon changes to be a box with an arrow pointing inward, with the tool tip: “Connects this panel with the frame.” Click on the box with the inward arrow to reconnect the panel with the frame. This will return the floating pane back to where it was last connected within the main VERDI window.

You can rearrange the panes within the main VERDI window. Click on the tab at the bottom of a frame and slide it along that area to change the order of the frames. Or slide it up or down and arrange the frames vertically so you can see more than one at a time. You can also click and hold a tab to slide its pane next to the other panes, consuming space that had been used by the charts pane. If you have the three panes beside each other – or two panes with tabs next to the third pane – you can easily change their relative position. Click on the title of the frame that you want to move, drag it, and then release it.

You can also change the amount of the entire VERDI window that is devoted to the 3 panes on the left vs. the charts pane on the right. Position your cursor along the line dividing these two sets of panes such that the cursor becomes a horizontal arrow pointing both left and right. Drag the cursor to the left to reduce the size of these panes and increase the size of the chart pane, or to the right for the opposite effect.

5 Navigating VERDI's Main Menu Options

Table 5-1 lists the main menu options that are available on the top menu bar in VERDI's main window (see Table 5-1). These options are discussed in detail below.

Table 5-1. VERDI Main Menu Options

File	Plots	Window	Help
Open Project	Undock All Plots	Areas	VERDI Help
Save Project	Animate Tile Plots	Datasets	About
Save Project As		Formulas	
View Script Editor			
Exit			

5.1 File Menu Options

5.1.1 Open Project

Open Project retrieves projects that were saved during a previous session (using the two **Save Project** options described in Section 5.1.2). Note that when you use a saved project, *it is very important* to load that project into VERDI *before* you load any additional datasets or create any additional variables/formulas. If you have already loaded datasets and then try to open a previously saved project, VERDI will show you a message that says “All currently loaded datasets will be unloaded” and will ask if you want to continue.

5.1.2 Save Project

The **Save Project** and **Save Project As** options save dataset lists and associated formulas as a “project” for later use.

Note that plots are not saved with a project; only datasets and formulas are saved. If you wish to save a plot configuration for later use, see Chapter 11 section on Saving Plot Configurations ([Chapter 11](#)).

5.1.3 View Script Editor

Use the **View Script Editor** to modify and run batch scripts within VERDI. Several sample script files are provided with the VERDI distribution under the \$VERDI_HOME/data/scripts directory. Use the Open popup window to specify file_patterns.txt, which is one of the sample script files. The contents of the file_patterns.txt will be displayed in the Script Editor in the right side of the VERDI window. Modify it to specify the local directory path name for the sample data files, the formulas, the type of plots, and the image format. The plots are not rendered within VERDI, but may be viewed using an image viewer. The batch scripting language is described in the sample script files, and is described in more detail in [Chapter 17 VERDI Batch Script Editor](#)

5.2 Plots Menu Options

VERDI opens a single pane for plots, to the right of the **Dataset**, **Formula**, and **Area** tabbed pane. Each plot is created in its own pane and is placed in the plot pane. The most recent plot is displayed on the




Figure 9: Selected plots must have matching time steps

top. Each plot has a tab beneath it listing the type of plot and the formula used to create it. If you want to view a previously created plot, select the tab associated with its pane underneath the current plot; the selected plot is then displayed on top.

5.2.1 Undock All Plots

As with the **Dataset**, **Formula**, and **Area** panes (Section 4.3), plot panes can be undocked or externalized so that you can move them into separate, floating windows. This allows side-by-side comparisons of plots. Note that undocking is performed only on previously created plots; each plot is placed within the VERDI main window when it is generated.

5.2.2 Animate Tile Plots

This option opens an **Animate Plots** dialog box PDF:(Fig- 9)) or GitHub:(Figure 9) that allows you to select one or more plots, select a subset of the time range, and create an animated GIF file. There is also a separate way to create a QuickTime movie instead of a GIF, if desired.

Within the **Animate Plots** dialog box, you can **select plot(s)** to animate by clicking the check box beside each plot name.

You can choose to animate a single plot, or animate multiple plots synchronously. To view multiple animated plots synchronously, undock the plots (see Section 5.2.1) and arrange them so that they are located side by side for visual comparison during the animation. NOTE: The underlying number of time steps must match or the Start button will not activate (PDF:(Fig- 9)) or GitHub: [Figure 9](#)).




Figure 10: Animate Plots Dialog and Tile Plots

After selecting your plots, **select the time range** by specifying both the **starting time step** and **ending time step** of the animation. The selected plots animate together over the selected time interval.

To create an animated GIF, check the **Make Animated GIF(s)** option in the **Animate Plots** dialog box. In the **Save** dialog box that appears, select the directory in which to store the file and the name to use for the animated GIF, then click the save button. When saving as an animated GIF, when multiple plots are selected, each animated plot will be saved to a separate animated GIF file. For example, if three plots were selected, the animated plots would be saved as <filename>-1.gif, <filename>-2.gif, <filename>-3.gif. You can view the animated GIF by opening the file in a web browser. see (PDF:(Figure 10)) or GitHub: [Figure 10](#))

Creating a QuickTime movie is also an option, but this is not done through the **Plots>Animate Tile Plots** main menu option. Instead, use the **Plot** menu option found at the top of each individual plot to make a QuickTime movie.

5.3 Window Menu Options

The **Window** menu provides an alternate way to select windows/panes to be brought to the front, and provides the same function as clicking on the tabs at the bottom of the windows/panes.

5.3.1 Datasets, Areas, and Formulas

Select from the **Window** pull-down menu to bring to the front either the **Datasets** pane, **Areas** pane, or **Formulas** pane when those panes are docked.

5.3.2 Script Editor

This option appears in the Window menu if you have a script editor window open. You can select this menu item instead of pressing the Script Editor tab at the bottom of its pane.

5.3.3 List of Plots

The **Window** pull-down menu is automatically updated each time a plot is created or removed in a VERDI session; each entry in the plot list indicates the type of plot and the formula used (e.g., Tile O3[1]). A check mark to the left of a plot designates the active plot. Click on a plot entry to bring that plot to the front for viewing. Alternatively, you can bring a plot to the front by selecting the desired **plot tab** underneath the plots area of the main window or by clicking on the plot's window for undocked plots. As in the menu entries, each **plot tab** is labeled with the plot type and the formula used.

5.4 Help Menu Options

The **Help** pull-down menu contains two items that you can use to learn more about VERDI. When you select **VERDI Help Documents**, you can select to view either the user manual or the developer instruction in your PDF-compatible reader. When you select **About** a popup window that contains the name of the product, the version number, and the date the software was built is displayed.

6 Working with Gridded Datasets

6.1 Gridded Input File Formats

6.1.1 Model File Format Conventions

VERDI currently supports visualizing files in the following file format conventions: CMAQ Models-3 Input/Output Applications Programming Interface (I/O API) netCDF, WRF netCDF, CAMx (UAM-IV), MPAS netCDF, and ASCII format (for observational data). VERDI uses a customized version of the thredds/NetCDF Java library v4.5.5 (<http://www.unidata.ucar.edu/software/netcdf-java>).

The CMAQ Models-3 I/O API was designed as a high-level interface on top of the netCDF Java library. (see <https://www.cmasccenter.org/ioapi/> and <http://www.unidata.ucar.edu/software/netcdf/> for further information). The Models-3 I/O API library provides a comprehensive programming interface to files for the air quality model developer and model-related tool developer, in both FORTRAN and

Timestamp (UTC)	LONGITUDE (deg)	LATITUDE (deg)	STATION (-)	pm25 (ug/m3)
2005-08-26T00:00:00-0000	-121.7842	37.6875	060010007	11.0000
2005-08-26T00:00:00-0000	-122.3991	37.7660	060750005	12.0000
2005-08-26T00:00:00-0000	-122.2034	37.4829	060811001	21.0000
2005-08-26T00:00:00-0000	-121.8950	37.3485	060850005	16.0000
2005-08-26T01:00:00-0000	-121.7842	37.6875	060010007	21.0000
2005-08-26T01:00:00-0000	-122.3991	37.7660	060750005	22.0000
2005-08-26T01:00:00-0000	-122.2034	37.4829	060811001	19.0000
2005-08-26T01:00:00-0000	-121.8950	37.3485	060850005	20.0000
2005-08-26T02:00:00-0000	-121.7842	37.6875	060010007	28.0000

Figure 11: Example observational data file showing format

C/C++. Models-3 I/O API files are self-describing and include projection information within the gridded dataset. See Chapter 12 for additional information on what projections and gridded data file format conventions are currently supported by VERDI.

NetCDF and Models-3 I/O API files are portable across computing platforms. This means that these files can be read regardless of what computer type or operating system you are using. Routines are available to convert data to these formats or new code can be written and contributed to VERDI for use by the community. Discussion of the Models-3 I/O API conversion programs and how to use them can be found in Chapter 13, “Models-3 I/O API Utilities, Data Conversion Programs, and Libraries.” If you write a routine for VERDI to read gridded data from other formats, please consider contributing your code to the user community using GitHub, as described in Chapter 14.

6.1.2 Observational Data Formats

VERDI can use observational data in either using ASCII file or created using Models-3 I/O API. An ASCII file needs to have data in tab-separated columns. The first four columns need to be in the order shown in PDF:(Fig- 11) or GitHub:[Figure 11](#). VERDI allows the user to specify an alphanumeric value (either numbers and/or letters) for the fourth column (Station ID). One or more additional columns must have the header format ‘name(units).’ Spreadsheet programs can be used to edit and write the files by choosing ASCII output; be certain to designate **tab** as the delimiting character (instead of comma). Data within a column must be complete, because empty fields prevent VERDI from reading the observational data.

Observational data in ASCII format can be obtained from many data sources. Data can be downloaded from the CMAS Center Google Drive (https://drive.google.com/drive/u/1/folders/1YIcmYtPH_DRyN51dDEQDh3r5Q) or EPA’s Remote Sensing Information Gateway - RSIG (<https://www.epa.gov/hesc/remote-sensing-information-gateway>). To use a consistent set of units for the model data and the observational data, you may need to import the ASCII data into a tool (e.g., a spreadsheet or database program) and perform a unit conversion. VERDI doesn’t allow the user to use an observational variable to create a formula, so conversions to different units must be performed before loading the data into VERDI.

Alternatively, you can use a converter such as AIRS2M3 (see Chapter 13) to convert ASCII observational data into Models-3 I/O API “observational-data” files.

6.2 Example Datasets

Several example datasets are provided under the \$VERDI_HOME/data directory. For example:

- Windows: %VERDI_HOME%\data
- Mac: \$VERDI_HOME/data/
- Linux: \$VERDI_HOME/data

These datasets may be used to recreate example plots that are provided in this user's manual, including a tile plot with observational data overlay (see Section 11.6.3.1) and example datasets for the various projections that VERDI supports including Lambert Conformal Conic (LCC), polar stereographic, Universal Transverse Mercator (UTM), and Mercator. The data directory currently contains seven subdirectories:

1. CAMx – contains sample CAMx dataset and camxproj.txt file
2. configs – contains sample config and theme files
3. hucRegion – contains Hydrologic Unit Code (HUC) shapefiles for region 3 (southeast US)
1. model – contains sample WRF netCDF, MPAS netCDF, and CMAQ Models-3 I/O API datasets
2. obs – contains an ASCII formatted observational dataset (Section 6.1.2), and an observational dataset created by airs2m3 converter (Chapter 13).
3. plots – contains sample plots created by VERDI
4. scripts – contains sample batch scripts

6.3 Adding and Removing a Dataset from a Local File System

To load a data set from a local file system, press the yellow **plus** button at the top of the **Datasets** pane. A file browser PDF:(Fig- 12) or GitHub:(Figure 12) allows you to select a dataset for use in VERDI. Support for loading data from a remote file system was added beginning in version 1.4. The use of the yellow **plus remote** button will be discussed in Section 6.4.

After you select a dataset, VERDI loads header information and displays the available variables, time steps, layers, and domain used by the file in the **Datasets** pane PDF:(Fig- 13) or GitHub:(Figure 13). (The actual model data are not loaded until later, when plots are created.) To view the variables for a particular dataset that has been loaded, click on the dataset name in the list to highlight it, and the variables will be listed in the panel below.

Datasets can be removed by highlighting the name of the dataset in the dataset list and pressing the yellow **minus** button. Note that although the dataset will be removed, the number that was assigned to that dataset will not be reused by VERDI during the current session (unless there had been only one dataset loaded, and it was removed; in that case the next dataset that is loaded will be labeled number 1).




Figure 12: Open Dataset File Browser




Figure 13: Datasets Pane Displaying Information about a Dataset

6.4 Adding and Removing a Dataset from a Remote File System

VERDI provides users with the ability to select and add variables from datasets on remote file systems. To do this, press the yellow **plus remote** (plus with a diagonal arrow) button at the top of the **Datasets** pane. In the Remote File Access Browser PDF:(Fig- ??)) or GitHub:(Figure 14) that appears, enter your user name, choose a host from the list, and enter your password, then click **Connect**.

6.4.1 Remote File Browser

The top panel displays a listing of the home directory on the remote file system, as shown in PDF:(Fig- 15)) or GitHub:(Figure 15). The current path is displayed in the text box and users can edit this information to change to another directory. An alternate way to navigate between directories is using the middle panel. In the middle panel, double click on a directory name to go into that directory, or click on the “..” at the top of the middle panel to navigate up a directory. As you enter a directory, the contents of the directory will be displayed as a list in the middle panel. Directory names are followed by a “/” symbol, while filenames do not have a “/” symbol after them. View the variables within each file of interest by double clicking on the netCDF filename listed in the middle panel. NOTE: if the selected file has a format that is not supported by VERDI then the following message will be displayed in the bottom panel: “Not a valid NetCDF file.” For supported netCDF files, VERDI will provide a list of variables that are available within the file in the bottom panel labeled “Select one or more variables.” To select variables from the list, use your mouse to click on a single variable, or use either the Shift key with the mouse to select a contiguous list of variables, or the Control key with the mouse to select a set of individual variables. Once the variables that you would like VERDI to read are highlighted, click on the **Read** button.

The variables read from the remote dataset will be displayed in the dataset and variable browser in the same way that variables from a local dataset are added and displayed within VERDI. The subsetted local dataset names are identical to the file names on the remote host, except for an additional extension that enumerates how many times the remote files were read and saved locally by VERDI (i.e., filename1, filename2, filename3, etc.), as shown in PDF:(Fig- 16)) GitHub:Figure 16. To add variables from the same remote dataset, click on the **plus remote** button, and repeat the above procedure.

The Remote File Browser retains the login session and the directory that was last accessed by the user to facilitate ease of accessing remote datasets. VERDI increments the numerical extension to the dataset name to indicate that this subset file was created using the same remote dataset, but that the subset file with the new numerical extension may contain a different subset of variables. Note that VERDI does not check to see if the same variable from the same remote dataset has already been read. Also, subset files read in by VERDI are saved either to your home directory on your local file system (e.g., C:\Users\username on a Windows 7 computer), or to the location that is specified in the config.properties file using the verdi.temporary.dir setting. Refer to Section 6.4.2 on how to edit and save the config.properties file.

The files are saved on your local machine to facilitate project management. To be able to save and then load a project for future use, the files need to be saved on the local machine. To avoid filling up your local file system, regularly inspect the file list in the home or verdi.temporary.dir directory and manually delete unneeded subset files.




Figure 14: Available Hosts in the Remote File Access Browser




Figure 15: Select One or More Variables from Remote Dataset

Remote datasets can be removed from the dataset list in VERDI using the same procedure as for removing local datasets: highlight the name of the dataset in the dataset list and press the yellow **minus** button. Note that although the dataset will be removed from the dataset list, the number that was assigned to that dataset will not be reused by VERDI during the current session.

6.4.2 Adding Additional Remote Hosts

VERDI contains the RemoteFileUtility and ncvariable programs that enable VERDI to add your Models-3 I/O API netCDF or WRF netCDF dataset from a remote file system. A gzipped tar file is available in the \$VERDI_HOME directory.

1. The RemoteFileUtility c-shell script and ncvariable binary need to be installed either in /usr/local/bin by the System Administrator, or you can place it in a different location and specify that location in the configure.properties file located in your \$USER_HOME/verdi/ directory (see section 3.4 for the specific directory location that is used for each platform [Linux, Windows, Mac]). A template for the configure.properties file called configure.properties.TEMPLATE is provided in the distribution under the \$VERDI_HOME directory.
2. A README file provided with the software contains instructions on how to compile the source code if the binaries provided do not match your operating system.
1. Copy the file configure.properties.TEMPLATE to configure.properties. Edit the configure.properties file in the \$USER_HOME/verdi directory. Add the name or IP address of the Linux server, preceded by a comma, at the end of the list of machines defined as remote hosts in the configure.properties file, as shown in PDF:(Fig- 17) or GitHub:[Figure 17](#). You then need to restart VERDI in order for it to recognize a newly added remote host name.

6.5 Variables List

The variables list shows all of the variables contained in a loaded dataset see PDF:(Fig- 18)) or GitHub:[Figure 18](#). To display a variables list, select the name of the dataset of interest in the **Datasets** pane. Each of the variables in the list can be used to create a formula in the **Formula** pane that can then be used to create plots. VERDI allows the user to automatically add a formula by double-clicking on the name of a variable. This automatically creates a formula that contains the variable for the loaded dataset and makes it the default formula for making plots. In addition, you may right-click on the name of the variable to show a popup menu as shown in the middle of the figure. From this menu you can either add the variable as a formula, or you can to add it into the formula editor so that it can be used to compose more complex formulas. Formulas are described in more detail in Chapter 7.





Figure 16: Remote Dataset Labeled with Number at End of the Filename



```

lizadams@killdevil-login1:/nas01/depts/ie/cempd/public_html/cmas/verdi — vim — 146x49
# This file should be put in $USER_HOME/verdi/ subdirectory
# Please use double backslash for windows platform or slash for UNIX like platforms as file
# Please uncomment the following lines and modify them to suit your local settings

# Windows example settings format
#     VerdiApplication.java, used as initial "current" file location
#verdi.install.home=C:\\Program Files\\VERDI_1.5.0\\
# verdi.project.home=C:\\Program Files\\VERDI_1.5.0\\project
#   Tools.java, folder with configuration, if null uses {user.home}
# verdi.config.home=C:\\Program Files\\VERDI_1.5.0\\config

# Linux example settings format
#     see above
verdi.install.home=/Users/lizadams/1.5.0_workspace
# verdi.project.home=../../data/project
#     see above
verdi.config.home=../../data/configs
#   VerdiApplication.java, used as initial location of datasets
# verdi.dataset.home=../../data/model
#   VerdiApplication.java, used as initial location of VERDI batch scripts
verdi.script.home=../../data/scripts
#   Tools.java, used as VERDI_HOME if environment variable is not set

# WDT default area file folder
#     TargetFileCard.java, used as default location of HUC (area) datasets
verdi.hucData=../../data/hucRegion

# For VERDI to access remote big NetCDF data files; DataSetPanel.java, if exists used as location returned from readRemoteHosts()
verdi.remote.hosts=terrasc.epa.gov,vortex.rtpnc.epa.gov,garnet01.rtpnc.epa.gov,tulip.rtpnc.epa.gov
#     RemoteFileReader.java, if exists used as initial path on remote system
# remote.file.util=/usr/local/bin/RemoteFileUtility
#     RemoteFileReader.java, if exists used as secure shell command on remote system
# verdi.remote.ssh=/usr/bin/ssh

#     RemoteFileReader.java, if exists used as location on local machine for downloaded files
# verdi.temporary.dir=C:\\temp

```

Figure 17: Edit configure.properties File to Add a Remote Host

6.6 Time Steps and Layers Panels

The range that is available for the dataset is listed in the Time Steps or Layers Panel in parenthesis next to the label for the panel. [Figure 6-8](#) shows that the dataset has 25 time steps with the range displayed as: Time Steps (1-25). You can use a subset of the full time step range by clicking on the Use Time Range checkbox, and then using the Min and Max spinner controls to set a new minimum or maximum value, for example choosing time step 2 as the minimum time step and time step 4 as the maximum. When a tile plot is created, it will only display time steps 2-4. Detailed instructions for using the **Time Steps** and **Layers** panels are discussed in Chapter 9, “Subsetting Spatial and Temporal Data.”

6.7 Saving Projects

As noted in Section 5.1.2, lists of datasets and formulas can be saved as “projects” using the Save Project option in the **File** pull-down menu on the VERDI main window. Refer back to that section for discussion on saving new projects and loading existing projects. Note that the plots created in VERDI are not saved with the project.

7 Working with Formulas

All plots in VERDI are generated from formulas. A formula is used to compare or manipulate variables in one or more gridded datasets. A formula can be as simple as a single variable from one gridded dataset or it can be an equation that uses variable(s) from one or more gridded datasets. Formulas are




Figure 18: Right-Click on Variable in Dataset Pane

used to create visualizations that can assist with model performance evaluations, for example, or can help in comparing model results with observations.

7.1 Adding and Removing a Formula

After loading the desired gridded datasets, you can use the variables in them to create formulas. To use a variable to create a simple formula, double click on the name of the variable. This will add the formula <Variable Name>[<Dataset Number>] to the formula list in the **Formulas** pane—for example, O3[1]. To add a variable to the formula editor window, highlight the variable, **right click** on the variable name in the **Datasets** pane, and select **Add Variable(s) to Formula Editor**. To add all or a subset of variables from the **Dataset** pane to the formula editor window, click on the first variable to highlight it, hold the Shift key down and click at the last variable that you want to include, then right click and select **Add Variables(s)**. The formulas that are highlighted using this method will be added to the formula editor PDF:(Fig- 19)) or GitHub:(Figure 19).

After the variable names are added to the Formula Editor, click on the formula pane and use the cursor and the keyboard to type in the mathematical functions and operators where needed to create a valid formula (see Section 7.2 and Chapter 16). After the formula has been created in the Formula Editor, click the **Add** button to place it in the list of formulas available in the **Formula** pane.

To remove a formula from the formulas list, highlight the name in the list and press the yellow **minus** button. Note that removing a formula from the formula list does not remove plots that were created prior to the deletion of the formula.

7.2 Example Formulas

To examine the values of ozone in dataset 1, the formula would be “O3[1].”

To examine the difference in ozone between datasets 1 and 2, the formula would be “O3[1]-O3[2].”

To calculate the percent difference in ozone between datasets 1 and 2, the formula would be “(O3[1]-O3[2])100/(O3[2])”. *To identify all cells where the ozone concentration exceeds a certain value, you can use the Boolean operators to focus on ranges of your data that are of particular interest. A Boolean expression will evaluate to either True = 1 or False = 0. For example, to plot the cells in which the ozone values in dataset 1 exceed 0.080 ppm, you could use the formula “(O3[1]>0.080)O3[1].” In the resulting plot, each cell where O3[1] exceeds 0.080 will show the value of O3[1] for that cell; for all other cells the value shown will be zero.*

The notations that can be used in formulas to represent various mathematical functions, and the order of precedence of these functions, are listed in Chapter 16, “Mathematical Functions.”

7.3 Selecting a Formula for Plotting

You must select a formula before creating a plot. Check to see which formula is highlighted in the **Formula** pane, or look to the right of the plot buttons above the plots area of the main window to see




Figure 19: Adding Multiple Variables to Formula Editor

the selected formula. By default, VERDI designates the most recently added formula as the selected formula. To change the selected formula to a different one in the list, click on a formula in the list on the **Formulas** pane, and you will then see it displayed as the selected formula above the plots area.

7.4 Saving Formulas

Both formulas and datasets can be saved using the **Save Project** item in the **File** pull-down menu on the VERDI main window. Saving new projects and loading existing projects were discussed in Section 5.1.

7.5 Time Step and Layer Ranges

Instructions for using the **Time Steps** and **Layers** panels are discussed in Chapter 9 Subsetting Spatial and Temporal Data.

8 Working with Area Files

8.1 Area File Formats

Area files are defined in VERDI as shapefiles that contain area features such as watersheds and counties, or any other shapefile that consists of a set of closed polygons.

The shapefile format (ESRI, 1998) consists of four files.

1. The *.shp file contains the actual shape vertices.
2. The *.shx file contains the index data pointing to the structures in the .shp file.
1. The *.dbf file contains the attributes (e.g., unique county ID).
2. The *.prj file contains the map projection information associated with the polygons.

8.2 Example Area File

Shapefiles that contain closed polygons are used by VERDI to interpolate gridded data to geographic boundary regions to create Areal Interpolation Plots. Shapefiles containing state, county, or census block, for example, or any other shapefile containing polygon areas may be used in VERDI to calculate and map formulas to the user-selected geographic regions. An example shapefile containing the 8-digit HUC watershed boundary map for the Southeast (HUC 3) is provided in the VERDI release under the \$VERDI_HOME/data/HucRegion directory.

Examples of on-line data archives for these shapefiles include:

<http://datagateway.nrcs.usda.gov>

<https://www.census.gov/geo/maps-data/index.html>

8.3 Requirements for Shapefiles used in Areal Interpolation

Shapefiles for areal interpolation must use units of degrees (not meters) and should use the following datum: DATUM[“unknown,” SPHEROID[“SPHERE,” 6370000.0, 0.0], TOWGS84[0,0,0]

8.4 Adding and Removing an Area File

To load a shapefile, press the yellow **plus** button at the top left corner of the **Areas** pane PDF:(Fig- 20) or GitHub:[Figure 20](#). A file browser PDF:(Fig- 21)) or GitHub:[Figure 21](#) allows you to change directories and select a shapefile file for use in VERDI. Click on the shapefile name and click **Next**. The **Open Area** popup window is displayed next, allowing you to select the name of the field to read from the file. Use the pull-down menu and click on the Name Field PDF:(Fig- 22)) or GitHub:[Figure 22](#) to be used. Each shapefile has a projection file associated with it (e.g., myFile.shp also has myFile.prj). After specifying the Name Field, select **Finish**. The resulting plot will be in the same projection as the gridded information used in the plot.

8.5 Areas List

The shapefile name(s) are listed in the top panel of the **Areas** pane, and the name fields for the polygons provided in the shapefile(s) are listed in the panel underneath PDF:(Fig- 23)) or GitHub:[Figure 23](#). The actual model data are not loaded until the Areal Interpolation plots are created. As additional shapefiles are added, the name fields associated with each shapefile are appended to the bottom of the Areas list. Use the scrollbar on the right side of the **Areas** pane to view the additional name fields that are available. To remove a shapefile, click on the name of the shapefile and press the yellow **minus** button at the top left corner of the **Areas** pane.

8.6 Areal Interpolation

When you select the Areal Interpolation Plot, your selected formula is remapped over the polygon areas that are listed in the **Areas** pane. To select a subset of the polygon areas, and view the average and total values for selected formulas, see Section 10.2: Areal Interpolation Plot.

9 ‘Subsetting Spatial and Temporal Data

Both the **Dataset** pane and the **Formula** pane include the three panels discussed in Sections 9.1 through 9.3: **Time Steps**, **Layers**, and **Domain**, respectively. Section 9.4 then discusses the precedence rules for subsetting data that determine whether **Datasets** or **Formulas** take priority.




Figure 20: Areas Pane




Figure 21: Open Area File Browser




Figure 22: Open Area File: Select Name Field




Figure 23: Area Name Fields in Current Shapefile




Figure 24: Specify Time Step Range

9.1 Specify Time Step Range

The **Time Steps** panel PDF:Fig- 24 or GitHub:(Figure 24) displays the range of time steps included in a dataset. The maximum time-step range that can be used for a dataset or formula is specified in the **Min** and **Max** spinner controls. You can use these controls to select a subset of the available time-step range for plotting. Check the **Use Time Range** box above the spinner controls to tell VERDI to use the time-step range values you have specified when it creates a plot. By default, a plot initially displays data for the minimum time step specified in the **Time Steps** panel. The range of time steps shown in the **Time Step** spinner control at the top of the plot reflects the subset of time steps specified when the **Use Time Range** box is checked. The date and time of the time step displayed in the plot are shown below the x-axis labels. Subsetting a dataset’s or formula’s time-step range affect plots produced with those data. Section 9.4 describes the precedence rules.

9.2 Specify Layer Range

Information on the range of vertical model layers included in a dataset is displayed in the **Layers** panel PDF:Fig- 25 or GitHub:(Figure 25) . Use the **Min** and **Max** spinner controls to select a subset of the available layer data for plotting. Check the **Use Layer Range** box above the spinner controls to tell VERDI to use the layers you have specified. By default, a plot will initially display data for the minimum layer chosen in the **Layers** panel. The range of the layers available in the **Layer** spinner control at the top of the plot matches the subset of layers specified when the **Use Layer Range** box is




Figure 25: Figure25

checked. Subsetting a dataset’s or formula’s layer range affects plots produced with those data. Section 9.4 describes the precedence rules.

9.3 Specify Domain Range

Datasets contain data for cells over a particular geographic area. VERDI refers to this area as a *domain*. By default, the entire domain contained in a dataset is used in creating plots. Use the **Controls** menu and then the **Set Row and Column Ranges** selection to define a subset of this domain for plotting.

9.4 Rules of Precedence for Subsetting Data

Use the subsetting feature to combine variables from two or more datasets that originally contained different but overlapping time steps and layers. Select identical subsets of the data available in each dataset such that their time steps and layers match. Then you can select variables from those datasets to create a formula and plot the data. Because both the **Dataset** pane and the **Formula** pane have the **Time Steps** and **Layers** panels described above, precedence rules determine which pane’s settings take priority. It is important to understand these rules.

NOTE: You must check the appropriate boxes to have your selected ranges take effect.

- Dataset precedence: A subset of data specified in the **Dataset** pane takes precedence over any subset specified in the **Formula** pane. However, VERDI does not change the ranges displayed in the **Formula** pane when you select a subset on the **Datasets** pane. For example, if a dataset has a full time-step range of 0-48 and you select a time-step range of 2-40 on the **Dataset** pane, then the 0-48 time-step range that is listed for the formula in the **Formula** pane is not applicable. When you subsequently create a plot, the time-step range subset you chose in the **Dataset** pane (2-40) is displayed.
- Formula ranges: If you do not specify a subset for a particular data type (i.e., time steps or layers) in the **Dataset** pane, then any subsetting for that data type in the **Formula** pane takes effect.

10 Creating Plots

After creating a formula, you are ready to create and view some plots. The available plot types are shown on the buttons at the top of the VERDI main window: tile plot, areal interpolation plot, vertical cross section plot, time series plot, time series bar plot, scatter plot, and contour plot. All of these are described in this chapter. Note that not all datasets are appropriate for all plot types.

To generate a plot first highlight a formula in the list of formulas you have created in the **Formula** pane. You can also see the selected formula in the top right corner of the main VERDI screen (i.e., to the right of the plot buttons). Next, generate a plot by clicking on that plot type's button. If VERDI needs additional information to generate your chosen plot, a dialog box appears to prompt you for that information.

Each plot contains its own menu bar at the top of its window with options for configuring and exploring that type of plot. The menus may include **File**, **Configure**, **Controls**, **Plot**, and **GIS Layers**. The options for each of these menus are described in more detail in Chapter 11 Plot Menu Bar.

10.1 Tile Plot

The **Tile Plot** displays gridded data defined as time steps and layers. It can also display grid cell time aggregate statistics. PDF: ([Fig- 26](#)) or GitHub:[Figure 26](#) provides an example of the **Tile Plot** window.

Figure 26. Tile Plot Example

10.1.1 Time Selection and Animation Controls

At the top left of the Tile plot, the **Time Step** spin control can be used to change the time step by clicking the up or down arrow. Alternatively, highlight the value shown for the current time step, type in the desired value, and press the **Enter** key.

Buttons in the top right corner of the plot allow you to use play/stop, reverse, forward, and speed options to control the animation of the plot. Control the speed of the animation through the text box labeled **Slow**; the default delay is 50 milliseconds between frames. If that text box is not visible, expand the plot window's width by clicking with the left mouse button on the right edge of the window and




Figure 26: Tile Plot Example

dragging to the right. Enter a number in the box for the length of the delay and then press the **Enter** key. A larger plot with multiple map layers may require a shorter delay between frames than a small zoomed-in plot with few map layers.

10.1.2 Layer Selection

The Layer displayed for the plot can be controlled by clicking on the up or down arrow for the **Layer** spin control in the top center of the plot.

10.1.3 Grid Cell Time Aggregate Statistics

The pull down menu option labeled **Stats** provides the option to display grid cell time-aggregate statistics (e.g., per-cell minimum, maximum, mean, geometric mean, median, first quartile, third quartile, variance, standard deviation, coefficient of variance, range, interquartile range, sum, time step of minimum, time step of maximum, maximum 8-hour average, and hours of noncompliance). Although you are still able to use the spinners to change the time step, the values and the chart's colors do not change.

VERDI calculates the grid cell time aggregate statistics as follows: For each cell (i,j,k) in the currently selected domain (independent of neighboring cells), the aggregated statistical value is calculated over the currently selected time steps. In other words, the aggregated statistical value is calculated for the plotted formula for cells $(i,j,k,t_{\min} \dots t_{\max})$, with the number of time steps n , where $n = (t_{\max} - t_{\min} + 1)$.

- MINIMUM: $\min(\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max}))$
- MAXIMUM: $\max(\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max}))$
- MEAN: SUM / n
- GEOMETRIC_MEAN: $((\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})))^{(1/n)}$
- MEDIAN: value at 50th percentile of (sorted { $\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})$ })
- FIRST_QUARTILE: value at 25th percentile of (sorted ($\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})$)))
- THIRD_QUARTILE: value at 75th percentile of (sorted ($\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})$)))
- VARIANCE: $((\text{var}(i,j,k,t_{\min}) - \text{MEAN})^2 + (\text{var}(i,j,k,t_{\min}+1) - \text{MEAN})^2 + \dots + (\text{var}(i,j,k,t_{\max}) - \text{MEAN})^2) / (n - 1)$
- STANDARD_DEVIATION: $\text{VARIANCE}^{0.5}$
- COEFFICIENT_OF_VARIANCE: $\text{STANDARD_DEVIATION} / |\text{MEAN}|$
- RANGE: $\text{MAXIMUM} - \text{MINIMUM}$

- INTERQUARTILE_RANGE: THIRD_QUARTILE - FIRST_QUARTILE
- SUM: $\text{var}(i,j,k,t_{\min}) + \text{var}(i,j,k,t_{\min+1}) + \dots + \text{var}(i,j,k,t_{\max})$
- TIMESTEP_OF_MINIMUM: 0-based time step when cell contains its minimum value
- TIMESTEP_OF_MAXIMUM: 0-based time step when cell contains its maximum value
- HOURS_OF_NON_COMPLIANCE: number of time steps that the cell value exceeds a given threshold $|\{\text{Var}(I,j,k,t(i)) > \text{threshold}\}|$
- MAXIMUM_8HOUR_MEAN: Ma (M1, M2, ..., Mn-8) where $M_i = \text{mean}(\text{var}(i,j,k,t(i)), \text{var}(i,j,k,t(i)+1), \text{var}(i,j,k,t(i+2)), \dots, \text{var}(i,j,k,t(i+8)))$, for $i = 1..n-8$
- fourth_max: fourth highest value for each grid cell (used to obtain the 4th highest value of your rolling 8 hr maximum CMAQ output file)
- custom_percentile: default is $> .12$ (use the text box) value at custom th percentile of(sorted $(\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min+1}), \dots, \text{var}(i,j,k,t_{\max}))$)

10.2 Areal Interpolation Plot

The **areal interpolation** plot displays the interpolated value of the selected formula for each polygon in the selected area file. Compare the colors of the polygons to those shown in the legend, to see the relative values of the formula for each polygon area. The Areal Interpolation Plot includes several capabilities that are not available for other plot types, so these are described below, rather than in Chapter 11 Plot Menu Bar.

10.2.1 Options Menu

The Areal Interpolation Plot menu contains an **Options** menu to allow the user to change the map to display either the Area Averages PDF:(Fig- 27) or GitHub:(Figure 27), the Area Totals PDF:(Fig- 28) GitHub:(Figure 28), or the value of the formula contained in the Gridded Dataset (uninterpolated) PDF:(Fig- 29) GitHub:(Figure 29). The **Options** pull-down menu may also be used to display All area segments that are loaded in the area list, or to display only the area segments that are selected by highlighting the name field from the area list PDF:(Fig- 30) or GitHub:(Figure 30).

10.2.2 Areal Values for Polygon Segment

To view the area, total value, and average value for a selected polygon segment use the mouse cursor to hover over a polygon on the map. The values are shown at the bottom left of the information panel PDF:(Fig- 31) or GitHub:(Figure 31).




Figure 27: Areal Interpolation Plot: Area Average




Figure 28: Areal Interpolation Plot: Area Totals




Figure 29: Areal Interpolation Plot: Show Gridded Data




Figure 30: Areal Interpolation Plot: Show Selected Areas




Figure 31: Areal Values for a Selected Polygon

10.2.3 View and Export Areal Interpolation Plot Data in Text Format

To view the average and total interpolation values for selected formulas in a spreadsheet format, right click on the Areal Interpolation Plot and select **Area Information** PDF:(Fig- 32) or GitHub:(Figure 32), then click on the radio button next to All, to select all area regions, click on the Formula Name, then click on OK. The Area Information Spreadsheet contains four columns: the identification number from the name field for the polygon, the total area, average interpolated value, and total interpolated value PDF: (Fig- 33)) or GitHub:(Figure 33). At the top of the **Area Information** tab, the user may select **File>Export** to export the data to a spreadsheet file (Figure 34). The save popup window allows the user to specify with either a text (.txt) or comma-separated-values (*.csv) format, also known as a comma-delimited text file (Figure 35).

10.2.4 Export Areal Interpolation Plot Data to Shapefiles

At the top of the **Area Information** tab PDF:(Fig- 36) or GitHub:(Figure 36), the user may select **File>Export Shapefiles** to export the data to a shapefile. In the Save popup window PDF:(Fig- 37)) or GitHub:(Figure 37), input the name in the File Name field, and select file type: Shapefile (*.shp). The data provided in the Area Information report (i.e., name, total area, average value, total value) are exported to the shapefile. A GIS program such as User-friendly Desktop Internet GIS (uDig; <http://udig.refractions.net/>), an open-source Java program, or QGIS (<http://qgis.org/en/site/>) may be used to view the shapefiles generated by VERDI. The shapefiles are saved as five separate files that must be kept together as part of the ESRI format (*.shp, .dbf, .prj, .shx, and .fix). There are no units assigned to the data that are saved in the shapefile, so it is important for the user to keep a copy of the comma-delimited text file, or to keep some alternative text file that specifies the units for each data field.

10.3 Vertical Cross Section Plot

The **vertical cross section plot** allows you to show a slice of data PDF:(Fig- 38)) or GitHub:(Figure 38). A popup dialog box PDF:(Fig- 39)) or GitHub:(Figure 39) prompts you for information needed to create the plot. Enter either the column to be used (for an *x*-axis cross section) or the row to be used (for a *y*-axis cross section) in the plot. The current time step on the plot can be changed using the **Time Step** spinner control above the plot, which also changes the date and time shown in the bottom of the plot. There is also a **Column** spinner control to change the column number (or row number). The cross-section column number (or row number) is included in the title of the plot and changes as you change the spinner control.

10.4 Time Series Plot

The **time series plot** shows a line graph with the average values over time (Figure 40). The plot is made for the formula's selected domain, layer range, and time-step range. Each time step's data are averaged linearly to produce that time step's data point. The current layer can be changed using the **Layer** spinner control above the plot. The layer value listed in the title is updated when you change the layer.




Figure 32: Right Click on Area Plot

Area Information: DRYOX_N[1] (1, 1)

File

Area Information: DRYOX_N[1] (1, 1)

Name	Area (km2)	DRYOX_N[1] (kg)	DRYOX_N[1]_A (kg/hectare)
1315	5658.38434050896	24295.299	4.293681
1327	4517.340297232507	20979.955	4.6443157
1309	1904.1156421275293	8881.052	4.664135
1323	4394.539581212584	20308.246	4.6212454
1339	4106.715652683912	17286.227	4.209258
1363	1546.2970358313198	7484.6016	4.8403387
1384	5280.143705007377	26897.678	5.0941186
1372	1534.9417887454965	6786.978	4.421652
2220	9744.923296339746	32835.496	3.3694978
1389	3207.6620998844414	16537.137	5.155511
2222	2185.3123721549996	8540.771	3.9082613
1413	6299.966453170846	26559.135	4.2157583
2225	3373.9280370367483	12193.176	3.6139407
1404	2276.6516332328333	9307.507	4.088244
1417	3355.692452064106	15284.323	4.554745
1424	6173.504265627928	26991.078	4.3720837
1440	4379.134220601725	20332.229	4.642979
1473	2334.7802505662535	11956.992	5.1212497
1486	6085.506620610624	27568.72	4.5302258
1469	3087.0962621653107	14152.65	4.584454
1468	3734.9135064814936	14930.879	3.9976504
1443	2532.7375578157676	8613.673	3.4009337
1461	2618.965925796131	9094.851	3.4726877
1448	2928.2832605735425	9465.642	3.2324884
2232	5292.355608000654	13661.271	2.5813217
1526	1698.8355649584494	7819.1265	4.6026387
1491	4208.0303564634505	15216.295	3.6160138
1505	2217.3759696883976	8044.047	3.6277325
1545	6359.784945829492	29068.387	4.5706553
1537	3646.5112012747236	16419.758	4.5028677
1485	2711.955229380954	8375.645	3.0884154
1508	4035.2177271460914	11958.902	2.9636323
1569	3506.6646873289114	16469.916	4.696747
1553	4546.181824042358	14209.543	3.1255994
1502	2916.183998927327	9382.019	3.2172244
1531	4494.55431244175	14186.302	3.1563313
1601	6472.768208735124	25231.164	3.8980486
1616	2639.488172937004	9257.198	3.5071943
1607	2113.024859363581	9490.889	4.4916124

ArealInterpolation Area Information: DRYOX_N[1] (1, 1)

Figure 33: Area Information in Columns

Area Information: DRYOX_N[2] (0, 0)			
File		Area Information: DRYOX_N[2] (0, 0)	
Export		Export Shape Files	
rname	Area (km2)	DRYOX_N[2] (kg)	DRYOX_N[2]_A (kg/ha)
1315	5655.875740826468	2433536.5	4.302669
1327	4515.625631195322	2046187.5	4.5313487
1309	1903.3636596603767	966721.5	5.0790167
1323	4392.830729537164	2160675.8	4.918641
1339	4105.370007776452	1804585.9	4.395672
1363	1545.727366164398	704919.7	4.56044
1384	5278.531687088094	2507917.2	4.7511644
1372	1534.467680366486	667539.25	4.3502984
2220	9742.857916457127	3446319.2	3.5372775
1389	3206.723523436829	1596897.2	4.9798403
2222	2184.7607501077305	902749.25	4.132028
1413	6298.539515028009	2538349.5	4.030061
2225	3373.2908771270318	1293966.2	3.835917
1404	2276.128379094424	963203.0	4.2317605
1417	3355.0225950614754	1514861.4	4.5152044
1424	6172.757287822339	2985992.2	4.837372
1440	4378.35502573675	2168069.5	4.9517903
1473	2334.434805271438	1042260.25	4.464722

Figure 34: Export to a Text File




Figure 35: Name and Save the Text File

Area Information: DRYOX_N[2] (0, 0)			
File	Area Information: DRYOX_N[2] (0, 0)		
Export	Export Shape Files	Area (km2)	DRYOX_N[2] (kg)
1315		5655.875740826468	2433536.5
1327		4515.625631195322	2046187.5
1309		1903.3636596603767	966721.5
1323		4392.830729537164	2160675.8
1339		4105.370007776452	1804585.9
1363		1545.727366164398	704919.7
1384		5278.531687088094	2507917.2
1372		1534.467680366486	667539.25
2220		9742.857916457127	3446319.2
1389		3206.723523436829	1596897.2
2222		2184.7607501077305	902749.25
1413		6298.539515028009	2538349.5
2225		3373.2908771270318	1293966.2
1404		2276.128379094424	963203.0
1417		3355.0225950614754	1514861.4
1424		6172.757287822339	2985992.2
1440		4378.35502573675	2168069.5
1473		2334.434805271438	1042260.25

Figure 36: Export Shapefile




Figure 37: Name and Save Shapefile




Figure 38: Vertical Cross Section Plot




Figure 39: Vertical Cross Section Dialog Box




Figure 40: Figure40




Figure 41: Time Series Bar Plot

10.5 Time Series Bar Plot

The **time series bar plot** shows average values over time in a bar plot format (Figure 41) rather than a line format (Figure 42). Other than that, the description of this plot type is the same as for the time series line plot (see Section 10.4).

10.6 Scatter Plot

The **scatter plot** shows the relationship between two formulas using dots PDF:(Fig- 42)) or GitHub:(Figure 42). Specify the formulas using the dialog box that comes up before the plot is displayed (Figure 43). The current time step and layer can be adjusted using the spinner controls above the plot. The data from a scatter plot may be exported by selecting the **File** menu option and then selecting Export data. If your dataset has more than one layer or time step, a popup window (see PDF:GitHub:Figure 44) allows you to specify whether you want to export the data for the current layer, or for all layers, and for the current time step, or for all time steps. Specify the time and layer ranges, and then click the **OK** button. A Save popup dialog box appears. Navigate to the directory in which you want to save this file and enter a file name with a .csv extension. The CSV file will be comma-delimited, and will contain the following columns of data: layer, time step, x-axis formula,




Figure 42: Scatter Plot

y-axis formula. You can open this file in a spreadsheet program if your data does not contain too many rows (e.g., 65,536 or 1,048,576 depending upon version of Microsoft Excel).

10.7 Contour Plot

The **contour plot** shows a three-dimensional (3-D) representation of values for a gridded dataset (e.g., one that can be used in the Tile Plot) PDF:(Fig- 45)) or GitHub:(Figure 45). Note that the 3-D contour plot is displayed in its own window (i.e., not in the VERDI window). The current time step and layer can be adjusted using controls above the plot. You can also animate the plot over time using an option in the **Plot** pull-down menu PDF:(Fig- 46)) or GitHub:(Figure 46). In addition, the contour plots can be rotated in three dimensions to achieve different viewing angles by using the left mouse button to grab and rotate the plot PDF:(Fig- 45)) or GitHub:(Figure 45).




Figure 43: Scatter Plot Dialog Box

11 Plot Menu Bar

Each VERDI plot contains a menu bar with options specific to that type of plot. The menu options at the top of the Tile Plot and Areal Interpolation Plot include those shown in [Table 11-1](#).

Table 11-1. Tile and Areal Interpolation Plot Pull-down Menu Options

File	Configure	Controls	Plot	GIS Layers
Print	Configure Plot	Zoom	Time Series of Probed Cell(s)	Add Map Layers
Export as Image/GIS	Load Configuration	Probe	Time Series Bar of Probed Cell(s)	Configure GIS Layers
	Save Configuration	Set Row and Column Ranges	Time Series of Min. Cell(s)	Set Current Maps as Plot Default
		Show Grid Lines	Time Series of Max. Cell(s)	
		Show Lat/Lon	Animate Plot	
			Add Overlay	

The menu options at the top of the Vertical Cross Section, Time Series, Time Series Bar Plot and Scatter Plot include those shown in [Table 11-2](#). Most options are common to all plots, and function in the same way (unless the option is grayed out). Therefore, this chapter is organized by menu instead of by plot type.




Figure 44: Scatter Plot Export Data into a CSV file




Figure 45: Contour Plot




Figure 46: Contour Plot Menu Options




Figure 47: Rotated Contour Plot

text file containing the cell values.

11.2 Configure Menu

The **Configure** pull-down menu contains the following options: Configure Plot, Load Configuration, and Save Configuration. When you want to see your changes on the plot, press the **Apply** button. When you have finalized the settings for your plot, click the **OK** button to close the Configure Plot dialog box.

11.2.1 Configure Plot

PDF:(Fig- 48) or GitHub:[Figure 48](#) through PDF:(Fig- 52) or GitHub:[Figure 51](#) show the dialog boxes that appear when you select Configure Plot. The **Configure Plot** dialog box contains four tabs: **Titles**, **Color Map**, **Labels**, and **Other**.

- **Titles tab:** PDF:(Fig- 48) or GitHub: [Figure 48](#) shows the selections on this tab that you can use to edit title text and select the font type, size, and color for the title and two subtitles of the plot. Subtitles may be turned on or off by selecting or deselecting the check box for each subtitle. If a check box is not selected the associated text, font type and size, and color boxes are grayed out. However, you must provide a title or VERDI will provide its default title for you. To blank out the title you must select it and then enter spaces for the name of the title. If you deselect the title VERDI will provide its default title for you.
- **Text:** Enter the desired text directly in the textbox. You can enter text for the plot's title and up to two optional subtitles.
- **Font:** Press the **Select** button to the right of the Font line for the title or subtitle you wish to change. Your system's standard Select Font dialog box is then displayed for you. Select a font family, font style, and size; press the **OK** button to return to the Configure Plot tab.
- **Color:** Press the **Select** button to the right of the Color line for the title or subtitle to edit. There are five types of color palettes that you can use to select a color – Swatches, HSV, HSL, RGB, and CMYK – each on its own tab. When you select a color examples of its use are shown in the Preview portion of the Select Color window. Select the **OK** button to accept the color and return to the Titles tab of the Configure Plot dialog box.
- **Color Map tab:** This tab is available for only the Tile and Areal Interpolation Plots (see PDF:(Fig- 49) or GitHub:[Figure 49](#)). This tab provides many widgets for you to configure your legend colors, break points, range, etc. You can select the number of tiles, the palette type to be used, the color interval, the number format, and the scale.




Figure 48: Configure Plot, Titles Tab




Figure 49: Configure Plot, Color Map Tab

- **Number of Tiles:** Start by selecting the number of tiles at the top of the pane. Options in some other selections, such as the available palettes and break points, change as you vary the number of tiles.
- **Palette Type:** Three palette types are available: Diverging, Qualitative, and Sequential. Diverging has dark colors at the maximum and minimum of the range and light colors in the middle. Qualitative has a mixture of colors. Sequential has a dark color on one end (typically the maximum) with lighter shades of the same color proceeding to the lightest shade at the minimum. The color palettes frequently associated with air quality modeling results are the Tile Plot default and the Newton RGB palettes of the Sequential type.
- **Reverse:** The reverse button reverses the order of the colors in the selected palette. For example, if a sequential palette is used, the reverse button changes the color intensities such that the darkest color is at the minimum instead of the maximum of the scale.
- **Interval:** The interval can be set to either Automatic or Custom. The typical setting is Automatic, meaning that VERDI calculates the interval break points based on the minimum and maximum values in the dataset. Change the interval to Custom if you need to edit the values for Interval Start for each color tile.
- **Number Format:** To specify the number format used in the map legend, enter the format `leading non-digit[width].[decimals][E][0]`. Then click the Rebuild button. NOTE: If you use any character other than E or e, VERDI will display each value as a decimal followed by that character.

Explanation of the format:

[width]: sum of [decimals] + 1 for . + desired number of places before the .; is recomputed in code if too small

..: separator between the values for [width] and for [decimals]

[E]: optional; if present use scientific notation (e.g., 2.33E-2) otherwise display in regular decimal notation (e.g., 0.0233)

- **Scale:** Select either Linear or Logarithmic. The interval start values are automatically adjusted when you change the scale.
- **Min and Max:** The minimum and the maximum values are computed for the data to be plotted. If you set the Interval to Automatic, you can change the values for the minimum and maximum. Then, press the Rebuild button and the Apply button to see your changes both in the legend and on the map. You cannot edit the minimum or the maximum value if the Interval is set to Custom. Instead, directly edit the Interval Start values; the Interval Start value for the lowest interval is the minimum value.
- **Rebuild:** The Rebuild button is either active or inactive (i.e., grayed out) depending upon what other widgets are active. If you make changes and the Rebuild button is active, press it before continuing.
- **Labels tab:** PDF:(Fig- 50) or GitHub:[Figure 50](#)) shows widgets for you to edit more labels on your plot. There are four tabs through which you can edit the labels of the Domain Axis (x-axis), the Range Axis (y-axis), Legend, and Footer.

- **Domain Axis:** This tab has two parts: Label and Ticks. Use the Label panel the same way as the Titles tab (above) by editing the Text, Font, and Color. The Ticks panel allows you to change the labels associated with the ticks on the Domain Axis. The “Show Tick Labels” checkbox is typically checked, but you can uncheck it to not show any ticks or labels on this axis. Number allows you to decrease the number of tick labels. Note that you cannot increase the number of ticks via this screen and the values of the ticks do not change; you are effectively turning tick labels on/off via this checkbox. The Font and Color widgets work the same as for the Titles tab.
- **Range Axis:** All the widgets on this tab are the same as on the Domain Axis tab. You are just making the changes for the Range Axis. PDF:(Fig- 51) or GitHub:[Figure 52](#)) shows an example plot where the number of Tick Labels has been reduced in both the Range Axis and the Legend, but the number of tick labels has not been reduced in the Domain Axis.
- **Legend:** The Show Legend checkbox defaults to checked, which indicates that the legend should be shown. If you do not want a legend, uncheck that checkbox. All the widgets on this tab are the same as on the tabs for the axes. Use the Label part to designate and format the label that appears vertically in the left side of the legend box. The tick labels are for the boundaries between colors in the legend. If you uncheck the Show Tick Labels checkbox, the tick labels disappear from the legend.
- **Footer:** This tab is divided into three parts: Line One, Line Two, and Observational Data Legend. Lines One and Two are for the first and second lines of footers, respectively. VERDI automatically creates these lines for you, but you can either edit or remove them here. You cannot enter text for the Observational Data Legend if you do not have observational data on your plot.
- **Other tab:** As shown in PDF:(Fig- 52) or GitHub:[Figure 51](#)), use the widgets on this tab to enable or disable showing the grid lines, to select the color of grid lines, and to select the series color.

11.2.2 Save Configuration

If you have made changes to the configuration of a plot, and want to reuse that configuration for other plots, use the **Save Configuration** selection from the **Configure** menu. It is very important (1) to name the file in a manner that you will remember what it contains and (2) to save the file in a logical place so you will be able to find it when you need it.

The file name should indicate the formula name, the dataset, and the type of plot from which it was saved. Also, use the “.cfg” extension to indicate that it is a configuration file. An example file name is <FormulaName><DatasetFilename><PlotType>.cfg, or “O3_CCTM_base_tile.cfg.”

You may decide to keep your configuration files with projects to which they relate or in a common directory. When you save your configuration file, VERDI uses the value of verdi.config.home in your config.properties file as the default location. If you want to save the configuration somewhere else, browse to the location. Enter the file name and press the **Save** button.




Figure 50: Configure Plot, Labels Tab




Figure 51: Example Plot with Selected Tick Marks for Range Axis and Legend




Figure 52: Other Tab

When you choose to save your configuration, VERDI displays a popup box asking if you want to save the title/subtitles. Although the configuration files generated by VERDI look similar to HTML or XML files, they are just text files containing tags compatible with the parser in VERDI. You can look at the contents of these files in a plain text editor (e.g., Notepad), but be very careful if you decide to change their contents; you could make the file unusable.

11.2.3 Load Configuration

To load a plot configuration file, first create a new plot that is of the same type and uses the same formula as that within the configuration file. Then select the **Load Configuration** option from the **Configure** menu on that plot. An **Open File Dialog** window enables you to navigate to the directory in which you saved the configuration file. Select the file you need and press the **Open** button. The plot title (if saved), color map, and other plot configuration features are then applied to the plot.

Note that it is possible to load a saved configuration file that does not apply to the selected plot. VERDI may try to load what it can, which may result in something other than what you expected. Therefore, before loading a saved plot configuration check carefully to be sure the plot type and formula of the configuration file match those of the new plot.

You can also load configuration files in batch or command line scripts by setting the parameter config-File (e.g., configFile=C:\User\username\VERDI_2.1\data\configs\o3_10bin.cfg).

11.2.4 Load Chart Theme

A Chart Theme sets the background colors and fonts for a Vertical Cross Section, Time Series, Time Series Bar, and Scatter plot. A loaded theme applies to each of these types of plots when you create them. This allows the user to customize and make the plots uniform for publishing purposes.

To load a chart theme, select the **Configure** menu on the plot and then the **Load Chart Theme** menu item. An **Open** Dialog window enables you to navigate to the verdi.config.home directory set in your config.properties file under the verdi directory in your home directory. As an example, select the **white.theme** theme file and press the **Open** button. The plot title, color map, and other plot configuration features are then applied to your current plot.

11.2.5 Edit Chart Theme

To edit a chart theme, select the **Configure** menu on the plot and then the **Edit Chart Theme** menu item. An **Edit Chart Theme** dialog frame opens. The top part of the Dialog is shown in PDF:(Fig- 53) or GitHub:[Figure 53](#); use the slider to view the bottom portion of the Dialog as shown in PDF:(Fig- 54) or GitHub:[Figure 54](#). Click **Select** next to the Text item you would like to change and a Select Font Dialog opens PDF:(Fig- 55) or GitHub:([Figure 55](#)). To change the color of an item, click **Select** next to it, and a Select Color Dialog frame opens PDF:(Fig- 56) or GitHub:([Figure 56](#)). Click **Apply** at any time to see your changes. When you are finished click **OK** to close the Edit Chart Theme window.




Figure 53: Top Portion of Edit Chart Theme Window




Figure 54: Bottom Portion of Edit Chart Theme (Bg=background, Grdln=grid line)




Figure 55: Select Font in Edit Chart Theme Window




Figure 56: Select Color in Edit Chart Theme Window

11.2.6 Save Chart Theme

To edit a chart theme, select **Save Chart Theme** option from the Configure menu on the plot. A **Save** Dialog will open PDF:(Fig- 57) or GitHub:([Figure 57](#))

11.3 Controls Menu

The **Controls** pull-down menu contains the following options: Zoom, Probe, Set Row and Column Ranges, Show Grid Lines, and Show Lat/Lon.

11.3.1 Zoom

To zoom in and enlarge a subdomain of the plot, select the **Zoom** option. Then use your left mouse button to draw a rectangle around your region of interest on the plot. To zoom out click on the chart using your right mouse button to bring up the context menu PDF:(Fig- 58) or GitHub:([Figure 58](#)). Move your cursor over either Zoom Out or Max Zoom Out and press the left mouse button. The Zoom Out selection performs a step zoom and the Max Zoom Out selection zooms out to the full extent of the plot.

The selections in the context menu are a little different for the time series plot. Zoom In and Zoom Out open another level of menus where you can select Both Axes, Domain Axis, or Range Axis. The Auto




Figure 57: Save Dialog




Figure 58: Right-Click on Tile Plot to Zoom Out




Figure 59: Click on Plot to Probe: Data Value Shown in Lower Left of VERDI, Latitude/Longitude Values Shown in Lower Right

Range selection opens another submenu with the same 3 selections; use the Auto Range, Both Axes submenu to reset both axes to the full extent of both the domain and the range.

11.3.2 Probe

To determine the data value at a specific point or within a subregion, select the **Probe** option.

11.3.2.1 Probe at a Single Point

To probe a single data point, use the mouse to hover the cursor over a single point on the plot (e.g., one value on a time series plot, one grid cell on a tile plot); the coordinates of the point are shown in the lower right-hand side of the plot in the format (column, row) or (longitude, latitude) if you have selected Show Lat/Lon. Once you click on the grid point of interest, the value of the datum at that grid point is displayed in the lower left-hand area of VERDI main window PDF:(Fig- 59) or GitHub:(Figure 60) in the format (time step, layer, row, column):value.

11.3.2.2 Probing a Domain Region of Data




Figure 60: Data Window Showing Probed Values for Region of Interest

When you have Probe selected you can examine the values of a region of locations. Use your mouse to draw a rectangle on the plot by clicking on a location, dragging the mouse to the opposite corner of your desired rectangle, and then releasing the mouse button. VERDI will create a data window displaying the grid values and will place it in the plot area of the VERDI main window as a tabbed window PDF:(Fig- 60) or GitHub:(Figure 61). The File>Export menu option at the top of the spreadsheet allows you to save probed data as a comma-delimited text file (*.csv).

11.3.3 Set Row and Column Ranges

The **Controls>Set Row and Column Ranges** menu item displays a popup window that allows you to configure the minimum and maximum values used in the columns (**x-axis domain*) and rows (**y-axis range*) PDF:(Fig- 61) or GitHub: (Figure 62 and Figure 62). Specify the values and then click **OK** to redraw the plot.




Figure 61: Select Set Row and Column Ranges

11.3.4 Show Grid Lines

Use the Show Grid Lines selection on the Controls menu if you want to have grid lines overlaid on your plot. PDF:(Fig- 62) or GitHub: [Figure 63](#) shows one reason for wanting grid lines. There is a set of grid cells with relatively high ozone values for the selected time step and layer. By zooming in on the plot and then showing the grid lines, the individual cells can be identified for further analysis.

11.3.5 Show Latitude and Longitude

To view the latitude and longitude values for a point on the plot, select the Show Lat/Lon option on the **Controls** menu. Then, hover your cursor over a location to see its latitude and longitude. The lat/lon coordinates are displayed in the lower right-hand side of the window PDF:(Fig- 63) or GitHub: ([Figure 64](#)). The option to display the lat/lon coordinates may be selected, and works with either the Zoom or the Probe option.

11.4 Plot Menu Options

The **Plot** pull-down menu PDF:(Fig- 64) or GitHub: ([Figure 65](#)) contains the following options: Time Series of Probed Cell(s), Time Series Bar of Probed Cell(s), Time Series of Min. Cell(s), Time Series of Max. Cell(s), Animate Plot, and Add Overlay. NOTE: The Time Series of Probed Cells and the Time Series Bar of Probed Cells selections are grayed out until you select a grid cell or multiple grid cells using the Controls>Probe menu selection.

11.4.1 Time Series Plots

The Time Series of Probed Cell(s) and Time Series Bar of Probed Cell(s) allows the user to select a set of cells, and then produce a time series or time series bar plot of the chosen subset of probed cells. The Time Series of Min. [or Max.] Cell(s) option creates a time series plot using data for the currently selected formula at that formula's domain, layer range, and time step range. The minimum [or maximum] value of that formula over the domain and layer range at that time step is calculated by VERDI and used for each of the time step's data points. For examples of the Time Series Plot and the Time Series Bar Plot see PDF:(Fig- 53) or GitHub: [Figure 10-15](#) and [Figure 10-16](#), respectively.

11.4.2 Animate Plots

You can create an animated plot by selecting the Animate Plot option. The Time Series and Time Series Bar Plots do not have an Animate Plot option. The plots that may be animated include: Tile, Areal Interpolation, Vertical Cross Section, and Contour Plot. An Animate Plot dialog box PDF:(Fig- 65) or GitHub:([Figure 66](#)) appears, allowing you to save animations either as an animated GIF with a file extension of .gif or as a QuickTime movie with a file extension of .mov. This **Plot** menu option is plot-specific and so does not allow you to animate more than one plot at a time. To animate multiple plots, you will need to use the **Plots** pull-down menu at the top of the VERDI main window; see Section 5.2.2, “Animate Tile Plots.”




Figure 62: Show Grid Lines on a Tile Plot




Figure 63: Lat/Lon Values Shown in Lower Right of VERDI




Figure 64: Plot Menu Options




Figure 65: Animate Plot Dialog Box

11.4.3 Add Overlays

VERDI supports two types of overlays – observations and vectors. For both types of overlays you may need to add data from another data file onto the underlying plot.

11.4.3.1 Observational Data Overlays

It is useful to visually compare the results contained in model output datasets with the data points in observational datasets. You can do this by creating a Tile Plot of the model output and then overlaying it with observational data points. The observational dataset needs to be in a csv- or tab-delimited format or a Models-3 I/O API observational data format. See Chapter 13 for more information about how to convert AIRS observational data into this latter format.

Sample observational data are provided in the directory \$VERDI_HOME/data/obs so you can create a sample Observational Data Overlay Plot. Follow these instructions to create your plot.

- Load a model output dataset.
- Load an observational dataset. Note that an *OBS* label appears to the right of the dataset name in the **Dataset** pane.
- Double-click on a variable in an observational dataset and add it to the **Variable** pane. Note that an *OBS* label appears to the right of the dataset name in the **Variable** pane.
- Create a formula in the **Formula** pane using a variable from the **model output** dataset. Use this formula to create a tile plot. (NOTE: If you attempt to use a formula that contains a variable

from an observational dataset, the following error will occur: “Error while evaluating formula: Selected dataset is observational.”

- Select Add Overlay>Observations from the tile plot’s **Plot** menu to view observational data as an overlay on a tile plot.
- An **Observation** dialog box PDF:(Fig- 66) or GitHub: ([Figure 67](#)) appears containing the variables that are available in the observational dataset. Select the observational variable to overlay on the Tile Plot from the Observation Details list. Multiple observational dataset variables can be overlaid on a Tile Plot.
- You can control the appearance of the symbols representing the observational data. The stroke size controls the thickness of the line used to draw the symbols; the shape size controls their diameter. You can use up to six different open-area shapes—circle, diamond, square, star, sun, and triangle—to distinguish among multiple observational datasets. A circle is the default symbol shape.
- Select **Add Variable** and then **OK** to overlay the observational data on the tile plot PDF:(Fig- 67) or GitHub:([Figure 68](#)).

Repeat the above process to add multiple variables. To remove the symbols for a variable on an observational data overlay, or to reset their size, shape, or stroke thickness, reopen the **Observation** dialog by using Add Overlay>Observations, select the observational variable you want to adjust, and then change its stroke size, shape size, or symbol. You can also remove a variable or move it up or down in the list. When you are finished click the **OK** button.

The center of the observational data point corresponds to the lat/lon value that is provided in the Models-3 I/O API observational data file. If observations are collocated, they are placed on top of one another. If that happens you may want to select different symbols or sizes for each dataset and place them from largest on the bottom to smallest on the top.

11.4.3.2 Vector Overlays

Follow these instructions to add a vector overlay to a Tile plot. Typically, these are created to show wind speed and direction on a plot of gridded air quality data. The length of the calculated vectors is proportional to their magnitude.

- Create your Tile Plot.
- If the data for your vectors are not in the same dataset, load the correct one and select the formulas that you will need for the vectors.
- Select the Add Overlay>Vectors option from the tile plot’s **Plot** pull-down menu PDF:(Fig- 68) or GitHub:([Figure 69](#)).
- Select the two components of your vector in the Vector Overlay dialog box PDF:(Fig- 68) or GitHub:([Figure 69](#)). Typically, these are the East-West (u) and North-South (v) components of the wind. Assign the u component to Horizontal and the v component to Vertical.




Figure 66: Tile Plot Observation Dialog




Figure 67: Tile Plot with Observational Data Overlay




Figure 68: Vector Overlay Dialog Box

- Specify the Vector Sampling Increment value to specify how many vectors are displayed, for example for every vector (increment=1), every third vector (increment=3), every fifth vector (increment=5)
- Click the **OK button** and the vector overlays are displayed on the plot.

NOTE: At this time you cannot control how the vectors are displayed, and there is no option to remove the vectors from the plot. If you need to make a change, you must start again with your Tile Plot.

Currently, vectors are plotted in the center of the grid cell. UWIND and VWIND are typically obtained from METCRO3D, which are defined at dot points or cell corners. Plotting the wind vector at their calculated locations will be added to the Tile Plot in a future release.

An example of an ozone concentration Tile Plot with a wind vector overlay is shown in Figure PDF:Fig-69 or GitHub:Figure 70. The length of each vector is proportional to its length. The direction of the vector is calculated from the direction and magnitudes of its two components. This figure illustrates how the wind changes speed and direction in this portion of the modeling domain for layer 1, time step 1.




Figure 69: Wind Vector Overlay on an Ozone Tile Plot




Figure 70: Add Map Layers

11.5 GIS Layers

The **GIS Layers** menu contains the following options: Add Map Layers, Configure GIS Layers, and Set Current Maps as Plot Default. All map layers provided with VERDI are shapefiles.

11.5.1 Add Map Layers

Use the **Add Maps Layers** option in the **GIS Layers** menu to add maps to a Tile Plot or Areal Interpolation Plot PDF:(Fig- 70) or GitHub:(Figure 71). Note that all GIS layers must be shapefiles.

A selection of default maps—including World, North America, USA States, USA Counties, HUCs, Rivers, and Roads—can be selected or deselected by clicking on the respective menu selection. A check mark then appears or disappears next to the chosen map name, and the selected map appears on the plot.




Figure 71: Manage Layers Dialog Box

As of VERDI 1.6, the Tile Plot and Areal Interpolation Plot use the Shapefile format for all maps and GIS layers, the bin format is no longer used.

11.5.2 Configure GIS Layers

To show an additional map on the plot, select the **Configure GIS Layers** option in the **GIS Layers** menu. When you click on this item, a dialog box titled Manage Layers gives you the following options: Move Up, Move Down, and Remove Layer PDF:(Fig- 71) or GitHub:(Figure 72). The Edit Layer option has been greyed out.

- To rearrange the order in which the GIS layers are displayed on the plot, select a layer in the Manage Layers dialog box, and then select Move Up or Move Down. Click the **OK** button to reposition the order of that layer within the list. If the layers that you are selecting are boundaries and were created to have a transparent fill, then rearranging the order of the layers will not change the look of the boundaries on the plot.
- To remove a GIS layer from the plot, select that layer in the list and select Remove Layer. Then click the **OK** button to remove it.

12 Supported Grid and Coordinate Systems (Map Projections)

VERDI makes calls to the netCDF Java library to obtain the grid and coordinate system information about the data directly from the model data input files when the input data files are self-describing (CMAQ, SMOKE, WRF netCDF format files).

12.1 Models-3 I/O API Data Convention

For the Models-3 I/O API, support for Lambert conformal conic (LCC) map projection, Universal Transverse Mercator (UTM) map projection, and polar stereographic map projection was added in VERDI 1.1., and Mercator projection in VERDI 1.2. The grid projections listed on the following website are supported, although not all have been tested: <https://www.cmascenter.org/ioapi/documentation/3.1/html/GRIDS.html>




Figure 72: Figure12-1

Users that need VERDI to support other projections are encouraged to provide small input datasets as attachments to emails to the m3user listserv, or to github.com/CEMPD/VERDI/issues, for testing and to facilitate future development efforts. [Figure 12-1](#) through [Figure 12-4](#) illustrate sample plots generated for datasets with LCC, polar stereographic, Mercator, and UTM map projections, respectively.

12.2 CAMx Gridded Data Convention

The netCDF-java library used in VERDI includes support for CAMx UAM-IV binary files using a preset default projection. CAMx or UAM binary files contain information about the x and y offsets from the center of the projection in meters, but do not contain information about the projection. The projection information is available in separate diagnostic files, which are part of the CAMx output along with the UAM binaries ([Figure 12-5](#)).

The netCDF-java library writes the default projection information to a text file in the directory where




Figure 73: Figure12-2




Figure 74: Figure12-3




Figure 75: Figure12-4

```
*****
CAMx
*****
CAMx

Simulation start time/date : 0.    060428    06118
Simulation end time/date   : 0.    060429    06119
Time zone                  : 0
Max timestep (min)         : 15.
Met Input interval (min)   : 60.
Emiss Input interval (min) : 60.
Output interval (min)      : 60.
Grid Projection Type       : LAMBERT
LAMBERT: center lon/lat    : -97.000    40.000
LAMBERT: true latitudes    : 45.000     33.000
Master Grid X/Y Origin     : -2736.000 -2088.000
Master Grid cell size       : 36.000     36.000
Master Grid NCOL NROW NLAY : 148        112        19
```

Figure 76: Figure12-5

Lambert Conformal Conic:

```
GDTYP = 2
P_ALP <= P_BET are the two latitudes which determine the projection cone;
P_GAM is the central meridian.
(X_CENT,Y_CENT) are the lat-lon coordinates for the center (0,0) of the
Cartesian coordinate system. Coordinate units are meters.
```

Figure 77: Figure12-6

the CAMx binary (UAM-IV) file is located. You can then review and edit the projection information to make it consistent with the projection specified in the CAMx diagnostic text files. The definitions of the projection parameters used in the camxproj.txt file are defined using Models-3 I/O API format <https://www.cmascenter.org/ioapi/documentation/3.1/html/GRIDS.html>. You must edit the camxproj.txt file to match the grid description information provided in the corresponding camx.diag file. **Figure 12-6** shows the definition for the grid projection parameters for a Lambert conformal conic projection.

Figure 12-7 shows the values of the camxproj.txt after editing it to match the values of the camx.diag file (**Error! Reference source not found.**) using the definitions of the Models-3 grid parameters (**Error! Reference source not found.**). **Figure 12-8** shows the resulting Tile Plot of the CAMx sample dataset.

```
# Projection parameters are based on IOAPI. For details, see
www.baronams.com/products/ioapi/GRIDS.html
GDTYP=2
P_ALP=33.0
P_BET=45.0
P_GAM=-97.0
XCENT=-97.0
YCENT=40.0
```

Figure 78: Figure12-7




Figure 79: Figure12-8

12.3 WRF netCDF Data Convention

The WRF netCDF data convention is supported in VERDI. <https://www.mmm.ucar.edu/weather-research-and-forecasting-model> Figure 12-9. WRF Example Plot of Height in Meters on a 1km Texas Domain

12.4 MPAS netCDF Data Convention

The MPAS netCDF data convention is supported in VERDI <https://mpas-dev.github.io/>. Figure 12-10. MPAS Example Plot of 2 meter Temperature on World Map

Figure 12-11. MPAS Example Plot of 2 meter Temperature Zoomed in to California

13 Models-3 I/O API Utilities, Data Conversion Programs, and Libraries

As discussed in Section 6.1, routines are available to convert gridded input data to Models-3 I/O API format or new code can be written and contributed to VERDI for use by the community. The Models-3 I/O API routines that have been written to convert data into this format are discussed in this section. If you are unable to use the available routines to convert your data and have a gridded dataset that VERDI is unable to read, please contact VERDI support via m3user@listserv.unc.edu with a description of the dataset.

The Models-3 I/O API Interface contains an extensive set of utility routines. There are example conversion programs to convert data from different data formats into the Models-3 I/O API format. The Models-3 I/O API Utilities are command line programs that are easy to script for automating analysis and post processing. An example of a Models-3 I/O API Utility that may be useful to VERDI users is m3merge. This utility merges selected variables from a set of input files for a specified time period, and writes them to a single output file, with optional variable-renaming in the process. Another utility that you may find useful is m3xtract. This program allows you to extract a few species from a large file and save them to a smaller file on your local computer so you can explore them using VERDI. The Models-3 I/O API Related Programs and Examples can be found at the following web site: <https://www.cmascenter.org/ioapi/documentation/3.1/html/AA.html#tools>.

Airs2m3 is an example of a data conversion program that converts the standard AIRS AMP350 observational data format to the Models-3 I/O API format. The airs2m3 program requires the following inputs:

- The input AIRS AMP350 print format file name.
- The time zone conversion file (provided with the obs2api program - tzt.dat).
- Additional hour shift variable. The AIRS data are hourly averaged, and a 00 time flag represents the hour 00-01. You may wish to represent that data segment by the ending hour. In that case, a 1 should be entered here.




Figure 80: Figure12-9




Figure 81: Figure12-10




Figure 82: Figure12-11

- Starting year, month, day, hour (GMT) (e.g., 1997 07 10 12).
- Ending year, month, day, hour (GMT) (e.g., 1997 07 16 12).
- Name of output variable (8 characters max) (e.g., O3_OBS).

14 Contributing to VERDI Development

If you have made an improvement to VERDI’s source code or documentation, please consider contributing it back to the community. You can start by requesting update notifications from VERDI’s GitHub site: <https://github.com/CEMPD/VERDI/>.

Instructions on how to set up the Eclipse Development Environment and for running and building VERDI within Eclipse are available in the VERDI Developer Documentation on the official VERDI web site: <https://www.cmascenter.org/verdi/>. If you anticipate doing software development on VERDI, you should contact the members of the VERDI project via <https://forum.cmascenter.org/c/verdi>

VERDI developers will test contributions to the source code and review the applicable documentation changes for inclusion in future VERDI releases. Note that anything you contribute either must have the same license as the rest of VERDI (i.e., GPL) or must be placed in the public domain.

The CMAS Center Forum can be used to query known errors, bugs, suggested enhancements, or submitted code contributions using the following website: <https://forum.cmascenter.org/c/verdi> or the GitHub Issue list <https://github.com/cempd/verdi/issues>. First, search to see if your issue is already listed as a bug or request for enhancement. If you do not see a matching entry, please submit a new topic with your issue to the CMAS Center Forum <https://forum.cmascenter.org/c/verdi>.

15 Known Bugs

You are encouraged to review the VERDI FAQ <http://www.cmascenter.org/help/faq.cfm>, review the latest release notes, query the CMAS Forum <https://forum.cmascenter.org/> to search questions and answers, bug reports, and suggestions. Once a bug is identified through the CMAS User Forum, it will be added as an issue on the Github for the developers to prioritize and fix. <https://github.com/CEMPD/VERDI/issues>.

16 Mathematical Functions

All VERDI visualizations are the result of a formula evaluation. Formulas operate on the variables provided by the datasets. The simplest valid formula consists of a single variable; for example, “O3[1]” is the parameter O3 from current dataset 1. Using infix notation, you can construct more complicated formulas using the mathematical operators and functions listed below. (Note that the documentation below derives from the equivalent documentation for the Package for Analysis and Visualization

of Environmental data [PAVE], which is available at http://www.ie.unc.edu/cempd/EDSS/pave_doc/EntirePaveManual.html.)

Note that the Batch Script method does not support all of the mathematical functions that are supported within the VERDI GUI and/or the command line script options.

Listed in order of precedence, the functions and operators are:

1. abs, sqr, sqrt, exp, log, ln, sin, cos, tan, sind, cosd, tand, mean, sum, min, max

1. ** (power)
2. /, *
3. +, -
4. <, <=, >, >=
5. ==, !=
6. &&
7. ||

VERDI also supports the following constants:

1. E 2.7182818284590452354

1. PI 3.14159265358979323846
2. NROWS Number of rows in the formula's currently selected domain
3. NCOLS Number of columns in the formula's currently selected domain
4. NLEVELS Number of levels in the formula's currently selected domain

16.1 Unary Functions

Unary functions are passed a single argument. Depending on the argument and the function type, the function returns a single value or a matrix of data by performing the function on each cell of the arguments array. For example:

- **sqrt(4):** Returns 2.0.
- **sqrt(O3[1]):** Returns a matrix containing the square root of each value in the O3[1] variable's array.

The following functions return a matrix when passed a dataset variable:

- **abs:** Returns the absolute value of the argument
- **sqrt:** Returns the square root of the argument.
- **sqr:** Returns the square of the argument.
- **log:** Returns the base 10 logarithm of the argument.
- **exp:** Returns Euler's number raised the power of the argument.
- **ln:** Returns the natural logarithm of the argument.
- **sin:** Returns the sine of the argument. The argument is in **radians**.
- **cos:** Returns the cosine of the argument. The argument is in **radians**.
- **tan:** Returns the tangent of the argument. The argument is in **radians**.
- **sind:** Returns the sine of the argument. The argument is in **degrees**.
- **cosd:** Returns the cosine of the argument. The argument is in **degrees**.
- **tand:** Returns the tangent of the argument. The argument is in **degrees**.

The following functions return a single number in all cases when passed a dataset variable:

- **mean:** Average cell value for all cells in currently selected domain.
- **sum:** Sum of all cell values in currently selected domain.
- **min:** For each cell (i,j,k) in the currently selected domain, this calculates the minimum value for that cell over the currently selected time steps. In other words, the minimum value in cells $(i,j,k,t_{\min}..t_{\max})$.
- **max:** For each cell (i,j,k) in the currently selected domain, this calculates the maximum value for that cell over the currently selected time steps. In other words, the maximum value in cells $(i,j,k,t_{\min}..t_{\max})$.

16.2 Binary Operators

Binary operators are not passed a value but operate on the operands to their left and right. Typically, they return a matrix of data by performing the operation on each cell of the operand's arrays. If both of the operands are single numbers then these binary operators return a single number. For example:

- **O3[1] * 2:** multiplies each item in the O3[1] array by 2 and returns the result.

- **O3[1] * O3[3]**: multiplies each item in the O3[1] array by the corresponding item in the O3[3] array and returns the result. (Note that this assumes that the arrays are of equivalent shape.)
- **3 * 2**: multiplies 3 by 2.

The binary operators:

- **+** Returns the sum of the operands
- **-** Returns the difference of the operands
- ***** Returns the product of the operands
- **/** Returns the ratio of the operands
- ****** Returns the left operand raised to the power of the right operand

16.3 Boolean Operators

Boolean binary operators return either 1 or 0 in each cell of the resulting matrix. If the operands are single numbers, then a single 1 or 0 is returned. The Boolean binary operators:

- **<** Returns 1 if the left operand is less than the right operand, else 0
- **<=** Returns 1 if the left operand is less than or equal to the right operand, else 0
- **>** Returns 1 if the left operand is greater than the right operand, else 0
- **>=** Returns 1 if the left operand is greater than or equal to the right operand, else 0
- **!=** Returns 1 if the left operand is not equal to the right operand, else 0
- **==** Returns 1 if the left operand is equal to the right operand, else 0
- **&&** Returns 1 if both operands are nonzero, else 0
- **||** Returns 1 if either operand is nonzero, else 0

16.4 Time Step Index

A time step index can be specified after a variable name. For example, “O3[1]:0” is the value of the O3[1] variable at the first time step.

17 VERDI Batch Script Editor

To open the Script Editor, use File>View Script Editor ([Figure 17-1](#)). Prior running a batch script, remove all datasets from the dataset list. To remove a dataset, click on each dataset in the dataset panel and press the yellow minus button.

18 Command Line Scripting

The commands described in this section can be executed from the command line through either command line arguments or Windows batch files. In Linux, you can edit the verdi.sh script, adding the command options at the end of the last line of the script. If you are using Windows, edit the run.bat script, again adding the command options at the end of the last line, and submitting the script at the windows command line. An example syntax for all commands follows the format

<command> <command options>

where the “” at the end of the command is optional.

18.1 Example Command Line Script for Linux Users

Set an environment variable \$VERDI_HOME by using

```
setenv VERDI_HOME //home//a_username//VERDI_2.1
```

Where a_username is your username.

The following script options will read in the file as the first dataset, select O3[1] as the formula from dataset 1, and create a tile plot of the O3[1].

```
./verdi.sh -f "$VERDI_HOME/data/model/CCTM46_P16.baseO2a.36k.O3MAX -s O3[1] -gtype tile
```

Example script file (Note that quotes (as shown highlighted in red) may be needed around the entire list of parameters” :

```
#!/bin/csh -f
```

18.1.0.1 8hO3 Daily Max Plot

```
setenv DIR //home//training//verdi_2.0//data/OBS
```

```
../../verdi.sh
```

```
"-f $DIR/ACONC_O3_8hr.dmax
```

```
-f $DIR/AQS_overlay_2002_07.ncf
```

```
-configFile /home/training/config.txt
```

```
-s O3[1]
```

```
-s O38[2]*1000"
```

Note: Currently, the syntax for the command line script is slightly different than the syntax for the batch script. For example, the batch script method supports requesting a plot of hour 12 using the notation O3[1]:12, but the command line script option requires the variable name and time step be specified independently:

```
-s O3[1]
```

```
-ts 12
```

18.2 Example Command Line Script for Windows Users

Edit the run.bat script in the VERDI_2.1 directory by right clicking on the file and selecting edit.

Figure -. Location of run.bat script in Windows

The current run.bat in notepad contains a “%1” at the end that allows it to accept input following the run.bat script using the Windows run command. Unfortunately, this command does not accept directory names that have a space them, such as the “Program Files.” If you would like to enter the script command line options after run.bat, please move the data directory to C:\VERDI\data or some other similar location.

Enter the following in the Run command: cmd

When a command line window opens do the following:

```
cd C:\Program Files\VERDI_2.1\
```

```
run.bat “-f C:\VERDI\data\model\CCTM46_P16.baseO2a.36k.O3MAX -s O3[1] -gtype tile”
```

The other option is to place the script commands within the run.bat itself. Remove the “%1” statement at the end of the run.bat that is provided in the distribution, and add the script options that you would like to use. The following run.bat contains script options that will read in the file C:\VERDI_2.1\data\model\CCTM46_P16.baseO2a.36k.O3MAX, select O3[1] as the formula, and create a Tile plot. The changes that you need to make to the run.bat are highlighted in red.

```
cd .\plugins\bootstrap
```

```
SET JAVA=..\..\jre1.6.0\bin\java
```

```
%JAVA% -Xmx512M -classpath “./bootstrap.jar;./lib/saf.core.runtime.jar;./lib/commons-logging.jar;./lib/jpf-boot.jar;./lib/jpf.jar;./lib\log4j-1.2.13.jar” saf.core.runtime.Boot -fC:\VERDI_2.1\data\model\CCTM46_P16.baseO3[1] -gtype fasttile
```

Run the run.bat script by clicking on Start, then selecting Run, then either using Browse to find the run.bat or typing it in (**Error! Reference source not found.**).




Figure 83: Figure18-1




Figure 84: Figure18-2

Figure -. Submit run.bat script from Run command

Script commands that can be used for command line scripting (listed in alphabetical order) are described below. Adding support for these script commands in the Script Editor is planned for a future VERDI release.

[-alias <aliasname=definition>] defines an alias. You can define an alias by creating a definition using variable names and derived variables that are calculated using the mathematical operators described in Section 15: Mathematical Functions. The alias definition does not include the dataset name. The alias is treated like any other formula once the alias definition and the dataset to which it should be applied are specified. If you need to redefine an alias definition, you must first use the **-unalias** command. The alias definitions are saved to a verdi.alias file in the verdi subdirectory under your home directory. VERDI uses this type of optional file in your home directory to maintain a snapshot of the current aliases being used. The following warning will be reported if an alias is defined more than once: “WARNING: Alias <aliasname> already defined, new definition ignored.” You are also responsible for not making circular references. Use the **-printAlias** command to view what aliases are already defined. Note, you define an alias, VERDI will use that alias if you make a request to plot that variable again. If you are having issues with variable names being redefined, remember to check your verdi.alias file and remove it if needed.

[-animatedGIF<filename>] creates an animated GIF by doing an X Window Dump (XWD) of each of the time steps in the tile plot, then converting them to GIF images. If there are many time steps in the dataset, there will be a slight delay before you are again given control of the GUI.

[-avi<filename>] saves an animated plot of each of the time steps in the tile plot to the AVI video format.

[-closeWindow “<windowid>”] closes the window with the specified window ID.

[-configFile <configFileName>] specifies a configuration file for VERDI to use for configuring subsequent tile plots.

[-copyright] prints out copyright information for VERDI.

[-drawDomainTicks ON|OFF] turns the domain axis ticks on and off.

[-drawGridLines ON|OFF] turns the plot grid lines on and off.

[-drawLegendTicks ON|OFF] turns the ticks in the legend on and off.

[-drawRangeTicks ON|OFF] turns the range axis ticks on and off.

[-f [[host:]]<filename>] tells VERDI to load in this dataset and make it the currently selected dataset. All datasets will stay in memory.

[-fulldomain] sets the VERDI domain matching the currently selected dataset to be completely selected. The currently selected dataset is usually the most recently added dataset.

[-g <tile|fasttile|line|bar|contour>] instructs VERDI to create a plot using the specified type and the currently selected formula’s data.

[-gtype <tile|fasttile|line|bar|contour>] instructs VERDI to create a plot using the specified type and the currently selected formula’s data (note: tile and fasttile will both generate a fasttile plot starting with VERDI version 1.4).

[-help|fullhelp|usage**]** display the information on all the command line arguments available. Each of these three versions performs the identical function.

[-legendBins “<bin0,bin1,...,bin_n>”**]** causes VERDI to use the specified numbers as breaks between colors on subsequent plots. The value of this argument is a comma-separated list of numbers. For example, **-legendBins “1,10,100,1000”** will cause plots to be created with three colors that correspond to values of 1-10, 10-100, and 100-1000. To go back to the default method for determining breaks between bins, enter **-legendBins DEFAULT**.

[-level <level>**]** sets the level range of all formulas to the single level specified.

[-levelRange <levelMax> <levelMin>**]** sets the level range of all formulas to the range specified.

[-openProject <VERDIProjectName>**]** opens a previously save VERDI project.

[-mapName <pathname>/<mapFileName>**]** causes VERDI to use the supplied *map name* instead of the default map for tile plots.

[-printAlias**]** prints existing alias definitions.

[-project “<VERDIProjectName>”**]** save dataset lists and associated formulas as a “project” for later re-use.

[-QuickTime (NEW)**]** creates a QuickTime movie of the currently selected plot.

[-quit|exit**]** ends the VERDI session.

[-raiseWindow <windowid>**]** raises the window with the specified plot ID (i.e., brings it to the front).

[-s “<formula>”**]** loads the specified formula into VERDI’s memory, and makes it the currently selected formula.

[-save2ascii “<filename>”**]** export data to a tab-delimited data file suitable for reading into a spreadsheet application such as Excel.

[-saveImage “<image type>” <file name>**]** saves the most recently created plot. This command works for all plot types. Supported formats include PNG, BMP, TIF, and JPG.

[-scatter “<formula1>” “<formula2>”**]** creates a scatter plot using the two formulas specified. Note that the formulas for the two components should already have been loaded into VERDI, and they are case sensitive.

[-showWindow <>windowId> <timestep>**]** sets the time step of the window with the specified window ID to the specified time step. The time step must be within the allowable range for the dataset.

[-subDomain <xmin> <ymin> <xmax> <ymax>**]** sets the VERDI domain matching the currently selected dataset to the bounding box specified by its arguments. The currently selected dataset is the most recently added dataset. It is often handy to type **-subdomain** commands into VERDI’s standard input if you are trying to select a very precise subdomain (such as that needed for a vertical cross-section plot).

[-subTitle1 “<sub title 1 string>”**]** allow you to control a plot’s subtitles if desired. Subsequent plots will use the default subtitles, unless these arguments are used again.

[-subTitle2“<sub title 2 string>”**]** allow you to control a plot’s subtitles if desired. Subsequent plots will use the default subtitles, unless these arguments are used again.

[-subTitleFont <fontSize>] allow you to control the font size of the subtitle of a plot.

[-system “<system command>”] sends the specified command to the operating system’s command line.

[-tfinal <final time step>] sets the last time step for each formula’s time-step range to the specified step number, where the first step number is denoted by 0.

[-tinit <initial time step>] sets the first time step for each formula’s time-step range to the specified step number, where the first step number is denoted by 0.

[-titleFont <fontSize>] allows you to control the font size of the title of a plot.

[-titleString “<title string>”] sets the title for the next plot made to the specified title. Subsequent plots will use the default VERDI title, unless this argument is used again.

[-ts <time step>] sets the selected time step for each formula in VERDI’s memory to the specified step number, where the first step number is denoted by 0. This will remain the selected time step until you change it. It affects only tile plots and vertical cross-section plots.

[-unalias <aliasname>] is used to undefine an alias.

[-unitString “<unit string>”] can be used to override the default unit label used for plots. The default value comes from the dataset(s) themselves.

[-vector “<U>” “<V>”] creates a vector plot with U as the left-to-right vector component and V as the down-to-up vector component. There are no background colors used for this type of plot. Note that the formulas for the two components should already have been loaded into VERDI, and they are case sensitive.

[-vectorTile “<formula>” “<U>” “<V>”] creates a vector plot with the result of “**formula**” as the background tiles, U as the left-to-right vector component, and V as the down-to-up vector component. Note that the formulas for the three components should already have been loaded into VERDI, and they are case sensitive.

[-version] prints out information about the VERDI version being used on the standard output stream.

[-verticalCrossPlot X|Y <row/column> (NEW)] creates a vertical cross-section plot. You indicate whether this will be an x or y cross-section plot and what row or column to use as the base.

[-windowid] prints the window ID of the currently selected plot.

19 Areal Interpolation Calculations

Before calculating the average value for a polygon segment, the area for each polygon is calculated using the projection of the grid system loaded. The system then calculates the area of overlay between each grid cell and the polygon segment.

The total contribution of a value (concentration, deposition, rainfall, etc.) from each cell for a given polygon segment is calculated using the following equation:

TV i = sum (Orci * Vrc) where

Orci = Area of overlay of cell at row r and column c with segment i,

Vrc = value of cell at row r and column c, and

r and c iterate across the rows and columns of the grid.

The Average Value is calculated by dividing the total value by the area of the polygon segment:

AverageVi = TVi / Ai where

Ai = Area of the polygon segment i

20 Licenses for JAVA Libraries used by VERDI

VERDI has been developed using a number of open source Java libraries. Table 20-1 contains a list of the jar files or Java libraries that are used by VERDI, a link to where each library may be acquired, a link to the location where the license is referenced by the documentation for each library, as well as a link to each license. The distribution for VERDI contains a sub-directory called licenses. This directory contains a copy of the licenses for the open source Java libraries used by VERDI.

List of Java Libraries	Where to acquire software	Reference to Software License for Software	Link to license or the specific license number
JTS (java topology suite)	http://sourceforge.net/projects/jts-topo-suite/	http://www.vividsolutions.com/JTS/jts_frame.htm	http://www.gnu.org/copyleft/lesser.html
log4j-1.2.13.jar	http://www.unidata.ucar.edu/software/netcdf-java/		http://logging.apache.org/log4j/1.2/license.html
saf.core.runtime	http://safr.sourceforge.net	http://www.eclipse.org/stp/cf/saf/SAFcore.html	http://www.eclipse.org/legal/epl-v10.html
vecmath.jar	http://java3d.dev.java.net/	https://vecmath.dev.java.net/	http://www.gnu.org/licenses/old-licenses/gpl-2.0.html
geoapi	http://geoapi.sourceforge.net/	http://www.codeplex.com/GeoAPI/license	LGPL V2.1, Feb. 1999
Gt2	http://sourceforge.net/projects/geotools/	http://docs.codehaus.org/display/GEOTDOC/00+Source+License	http://www.gnu.org/licenses/lgpl-2.1.txt
hsqldb	http://hsqldb.org/		http://hsqldb.org/web/hsqLicense.html
jfreechart	http://sourceforge.net/projects/jfreechart/	http://developer.vrjuggler.org/browser/trunk/juggler/external/jfreechart/LICENSE.txt?rev=15441	LGPL V2.1, Feb. 1999

List of Java Libraries	Where to acquire software	Reference to Software License for Software	Link to license or the specific license number
jscience	http://jscience.org/	http://swik.net/Jean-Marie-Dautelle	http://swik.net/License:BSD/BSD+License+Text
Piccolo 1.2	http://www.cs.umd.edu/hcil/jazz/	http://www.cs.umd.edu/hcil/jazz/download/open-source.shtml	http://opensource.org/licenses/bsd-license.php
Ucar_ma2	http://www.unidata.ucar.edu/software/netcdf-java	http://www.unidata.ucar.edu/software/netcdf-java/	http://www.gnu.org/copyleft/lesser.html
Repast symphony GIS	http://repast.sourceforge.net/		http://repast.sourceforge.net/repast-license.html

Table - JAVA Libraries used by VERDI

21 Acknowledgments

Contributions to VERDI from the community are greatly appreciated.

21.1 Data Contributions

Sample CAMx Dataset

Marco Rodriguez, CIRA at Colorado State University <http://www.cira.colostate.edu/>

Sample Mercator Projection Dataset

Tanya Otte, Atmospheric Modeling and Analysis Division, <http://www.epa.gov/amad/index.html>

21.2 Data Reader Contributions

I/O Service Provider (IOSP) Interface for CAMx:

Barron Henderson, ORISE Fellow, EPA, Ph.D. student UNC Chapel Hill

Incorporating the IOSP into netcdf-java Library:

John Carron, Unidata, <http://www.unidata.ucar.edu/software/netcdf/index.html>

[1] Schwede, D., N. Collier, J. Dolph, M.A. Bitz Widing, T. Howe, 2007: A New Tool for Analyzing CMAQ Modeling Results: Visualization Environment for Rich Data Interpretation (VERDI). Proceedings, CMAS 2007 Conference.