

# VERDI 2.2 User Manual

8/13/2025

## Contents

<b>1</b>	<b>Introduction</b>	<b>6</b>
1.1	Background . . . . .	6
1.2	Where to Obtain VERDI . . . . .	7
1.3	Where to Obtain VERDI Documentation . . . . .	12
1.4	Help Desk Support for VERDI . . . . .	14
1.5	Future VERDI Development . . . . .	14
<b>2</b>	<b>Requirements for Using VERDI</b>	<b>14</b>
2.1	Java . . . . .	14
2.2	Memory and CPU Requirements . . . . .	14
2.3	Requirements to Run VERDI Remotely . . . . .	15
2.4	Graphics Requirements . . . . .	15
2.5	Display Properties . . . . .	15
<b>3</b>	<b>VERDI Installation Instructions</b>	<b>15</b>
3.1	Installation Instructions for Linux and Mac . . . . .	16
3.2	Installation Instructions for Windows . . . . .	17
<b>4</b>	<b>Starting VERDI and Getting Your Data into VERDI</b>	<b>19</b>
4.1	Starting VERDI . . . . .	19
4.1.1	Windows . . . . .	19
4.1.2	Linux and Other Non-Windows JRE Supported System Configurations . . . . .	19
4.2	Main Window . . . . .	19
4.3	Rearrange the Datasets, Formulas, and Areas Panes . . . . .	22

<b>5 Navigating VERDI's Main Menu Options</b>	<b>23</b>
5.1 File Menu Options . . . . .	23
5.1.1 Open Project . . . . .	23
5.1.2 Save Project . . . . .	23
5.1.3 View Script Editor . . . . .	23
5.2 Plots Menu Options . . . . .	24
5.2.1 Undock All Plots . . . . .	24
5.2.2 Animate Tile Plots . . . . .	24
5.3 Window Menu Options . . . . .	25
5.3.1 Datasets, Areas, and Formulas . . . . .	25
5.3.2 Script Editor . . . . .	25
5.3.3 List of Plots . . . . .	26
5.4 Help Menu Options . . . . .	26
<b>6 Working with Gridded Datasets</b>	<b>26</b>
6.1 Gridded Input File Formats . . . . .	26
6.1.1 Model File Format Conventions . . . . .	27
6.1.2 Observational Data Formats . . . . .	27
6.2 Example Datasets . . . . .	28
6.3 Adding and Removing a Dataset from a Local File System . . . . .	29
6.4 Adding and Removing a Dataset from a Remote File System . . . . .	31
6.4.1 Remote File Browser . . . . .	31
6.4.2 Adding Additional Remote Hosts . . . . .	34
6.5 Variables List . . . . .	34
6.6 Time Steps and Layers Panels . . . . .	36
6.7 Saving Projects . . . . .	36
<b>7 Working with Formulas</b>	<b>38</b>
7.1 Adding and Removing a Formula . . . . .	38
7.2 Example Formulas . . . . .	38
7.3 Selecting a Formula for Plotting . . . . .	40
7.4 Saving Formulas . . . . .	40
7.5 Time Step and Layer Ranges . . . . .	40

<b>8 Working with Area Files</b>	<b>40</b>
8.1 Area File Formats . . . . .	40
8.2 Example Area File . . . . .	41
8.3 Requirements for Shapefiles used in Areal Interpolation . . . . .	41
8.4 Adding and Removing an Area File . . . . .	41
8.5 Areas List . . . . .	41
8.6 Areal Interpolation . . . . .	42
<b>9 Subsetting Spatial and Temporal Data</b>	<b>42</b>
9.1 Specify Time Step Range . . . . .	42
9.2 Specify Layer Range . . . . .	42
9.3 Specify Domain Range . . . . .	48
9.4 Rules of Precedence for Subsetting Data . . . . .	48
<b>10 Creating Plots</b>	<b>48</b>
10.1 Tile Plot . . . . .	49
10.1.1 Time Selection and Animation Controls . . . . .	49
10.1.2 Layer Selection . . . . .	50
10.1.3 Grid Cell Time Aggregate Statistics . . . . .	50
10.1.4 Specify Layer Range when use ‘layer_sum’ and ‘layer_mean’ from the above aggregated Statistics dropdown menu in a tile plot . . . . .	51
10.2 Areal Interpolation Plot . . . . .	51
10.2.1 Options Menu . . . . .	52
10.2.2 Areal Values for Polygon Segment . . . . .	52
10.2.3 View and Export Areal Interpolation Plot Data in Text Format . . . . .	57
10.2.4 Export Areal Interpolation Plot Data to Shapefiles . . . . .	57
10.3 Vertical Cross Section Plot . . . . .	57
10.4 Time Series Plot . . . . .	57
10.5 Time Series Bar Plot . . . . .	66
10.6 Scatter Plot . . . . .	66
10.7 Contour Plot . . . . .	67

<b>11 Plot Menu Bar</b>	<b>68</b>
11.1 File Menu . . . . .	69
11.2 Configure Menu . . . . .	69
11.2.1 Configure Plot . . . . .	69
11.2.2 Save Configuration . . . . .	81
11.2.3 Load Configuration . . . . .	84
11.2.4 Load Chart Theme . . . . .	85
11.2.5 Edit Chart Theme . . . . .	85
11.2.6 Save Chart Theme . . . . .	85
11.3 Controls Menu . . . . .	85
11.3.1 Zoom . . . . .	85
11.3.2 Probe . . . . .	89
11.3.3 Set Row and Column Ranges . . . . .	93
11.3.4 Show Grid Lines . . . . .	93
11.3.5 Show Latitude and Longitude . . . . .	96
11.3.6 Show Cell Borders (MPAS files) . . . . .	96
11.4 Plot Menu Options . . . . .	96
11.4.1 Time Series Plots . . . . .	96
11.4.2 Animate Plots . . . . .	96
11.4.3 Add Overlays . . . . .	100
11.5 GIS Layers . . . . .	104
11.5.1 Add Map Layers . . . . .	104
11.5.2 Add Satellite Image Layer . . . . .	108
11.5.3 Configure GIS Layers . . . . .	108
<b>12 Supported Grid and Coordinate Systems (Map Projections)</b>	<b>109</b>
12.1 Models-3 I/O API Data Convention . . . . .	109
12.2 CAMx Gridded Data Convention . . . . .	114
12.3 WRF netCDF Data Convention . . . . .	117
12.4 MPAS netCDF Data Convention . . . . .	119
<b>13 Models-3 I/O API Utilities, Data Conversion Programs, and Libraries</b>	<b>123</b>

<b>14 Contributing to VERDI Development</b>	<b>123</b>
<b>15 Known Bugs</b>	<b>124</b>
<b>16 Mathematical Functions</b>	<b>124</b>
16.1 Unary Functions . . . . .	125
16.2 Binary Operators . . . . .	126
16.3 Boolean Operators . . . . .	127
16.4 Time Step Index . . . . .	127
<b>17 VERDI Batch Script Editor</b>	<b>127</b>
17.1 Specify hour/time step formula in batch script mode . . . . .	133
17.2 Mathematical function capability in batch script mode . . . . .	135
17.2.1 Batch Script Example: Maximum Ozone – layer 1 (Figure 100) . . . . .	136
17.2.2 Batch Script Example : Minimum Ozone – layer 1 (Figure 101) . . . . .	136
17.2.3 Batch Script Example : Mean of Ozone – layer 1 (Figure 102) . . . . .	138
17.2.4 Batch Script Example : Sum of Ozone – layer 1 (Figure 103) . . . . .	139
<b>18 Command Line Scripting</b>	<b>140</b>
18.1 Example Command Line Script for Linux Users . . . . .	141
18.1.1 8hO3 Daily Max Plot . . . . .	141
18.2 Example Command Line Script for Windows Users . . . . .	142
<b>19 Areal Interpolation Calculations</b>	<b>146</b>
<b>20 Visualize Fine Scale Model Outputs</b>	<b>147</b>
<b>21 Licenses for JAVA Libraries used by VERDI</b>	<b>151</b>
<b>22 Acknowledgments</b>	<b>152</b>
22.1 Data Contributions . . . . .	152
22.2 Data Reader Contributions . . . . .	152
22.3 Shapefile Export and High Resolution Background Map Contributions . . . . .	152

**Visualization Environment for Rich Data Interpretation (VERDI): User's Manual**

U.S. EPA Contract No. EP-W-09-023, "Operation of the Center for Community Air Quality Modeling and Analysis (CMAS)" Prepared for: Daiwen Kang U.S. EPA, ORD/CEMM/AESMD/ADMB E243-04 USEPA Mailroom Research Triangle Park, NC 27711

Prepared by: Liz Adams (UNC-IE) and Yadong Xu (USEPA) Date: Aug 13, 2025

## 1 Introduction

### 1.1 Background

This manual describes how to use the Visualization Environment for Rich Data Interpretation (VERDI). VERDI is a flexible and modular Java-based visualization software tool that allows users to visualize multivariate gridded environmental datasets created by environmental modeling systems such as the Community Multiscale Air Quality (CMAQ) modeling system, the Weather Research and Forecasting (WRF) modeling system, and Model for Prediction Across Scales (MPAS). These systems produce files of gridded concentration and deposition fields that users need to visualize and compare with observational data both spatially and temporally. VERDI can facilitate these types of analyses.

Initial development of VERDI was done by the Argonne National Laboratory for the U.S. Environmental Protection Agency (EPA) and its user community. Argonne National Laboratory work was supported by the EPA through U.S. Department of Energy contract DE-AC02-06CH11357. Further development has been performed by the University of North Carolina Institute for the Environment under U.S. EPA Contract No. EP-W-05-045 and EP-W-09-023, by Lockheed Corporation under U.S. EPA contract No. 68-W-04-005, by General Dynamics Information Technology under U.S. EPA contract No. GS00Q09BGD0025 and Argonne National Laboratory. VERDI is licensed under the GNU General Public License (GPL) version 3, and the source code is available through <https://github.com/CEMPD/VERDI>. Instructions for developers within the community are included in the VERDI Developer Instructions (see Section 1.3). VERDI is supported by the Community Modeling and Analysis System (CMAS) Center under U.S. EPA Contract No. EP-W-09-023. The batch script and VERDI Script Editor were developed and documented under U.S. EPA Contract No. EP-D-07-102, through an Office of Air Quality Planning and Standards project managed by Kirk Baker. The CMAS Center is located within the Institute for the Environment at the University of North Carolina at Chapel Hill.

This manual describes VERDI version 2.2 released in September 2025.

The following are useful web links for obtaining VERDI downloads and support:

1. VERDI Visualization Tool web site:

<http://www.cmascenter.org/verdi>

2. CMAS download page for users of VERDI (requires a CMAS account):

[https://www.cmascenter.org/download/forms/step\\_2.cfm?prod=11](https://www.cmascenter.org/download/forms/step_2.cfm?prod=11)

3. CMAS GitHub website for developers of VERDI:

<https://github.com/CEMPD/VERDI>

4. VERDI Frequently Asked Questions (FAQs):

<https://www.cmascenter.org/help/faq.cfm>

Use pulldown menu to select VERDI product to view its FAQs.

1. To query and ask questions use the new CMAS User Forum, by selecting the VERDI category:  
<https://forum.cmascenter.org/c/verdi>
2. To query the older M3USER listserv for VERDI related technical support questions and answers:  
<http://lists.unc.edu/read/?forum=m3user>
3. To query bugs and submit bug reports, questions, and/or requests:

<https://github.com/CEMPD/VERDI/issues>

## 1.2 Where to Obtain VERDI

You can download the latest version of VERDI from <https://www.cmascenter.org/verdi/> (PDF see (Fig-1) and (2)) (Github see: [Figure1-1](#) and [Figure 1-2](#)). When you click on DOWNLOAD to download VERDI, you will be sent to the CMAS Model Download Center. To download and install VERDI, follow the instructions below, beginning at step 4. Alternatively, you may also begin at the CMAS web site <https://www.cmascenter.org>, and follow the instructions below:

1. Log in using an existing CMAS account, or create a new CMAS account.
2. Click the Download drop-down list and choose SOFTWARE.
3. From the Software Download, Step 1 page go to the box Select Software to Download on the right side of the page. Use the drop-down list to select VERDI, and then click Submit.
4. Select the product you wish to download, as shown in [Figure 3](#) (Fig1- 3)). Also specify the type of computer on which you will run VERDI (i.e., Linux PC, Windows, or Other) from the items in the scroll list. Note that the compilers question is not relevant for VERDI so please select Not Applicable. Finally, click Submit.
5. As shown in [Figure 4](#) (Fig1- 4)) follow the links to the appropriate version of the Linux, Mac, or Windows installation files. Links are also available for the current version of the documentation.

**Community Modeling and Analysis System**

Search for...

Help ▾ Download ▾ Software ▾ Conference ▾ Training ▾ Resources ▾ User Details ▾ Log Out

HOME / VERDI / INDEX.2.2

# VERDI

**Visualize gridded netCDF data with this easy-to-use Java program.**

VERDI is a Java program for visualizing meteorology, emissions, and air quality modeling data. With options for overlaying GIS Shapefiles and observational data onto model output, VERDI offers a range of options for viewing atmospheric modeling data. VERDI scripting provides a powerful interface for automating the production of graphics for analyzing your data.

**Features:**

- Java**
- VERDI uses Java, which makes it easy to install and is portable across different operating systems.
- VERDI packages are distributed for 64-bit Windows, Linux, and Mac.
- GUI**
- The VERDI user environment is an intuitive GUI that makes importing datasets, creating formulas, and generating and saving plots easy.
- Supported Plot Types**
- VERDI currently can be used to create 2-D tile plots, vertical cross sections, scatter plots, timeseries line, timeseries bar, 3-D contour plots, vector-tile plots, areal interpolation plots, and observation-tile plots.
- Supported File Format Conventions**
- CMAQ Input/Output Applications Programming Interface (I/O API) netCDF, WRF netCDF, MPAS netCDF, CAMx (UAM-IV), and I/O API and text-based ASCII formats (for observational data).
- Scriptable**
- VERDI can be driven with a scripting language to allow batch-generation of images.
- VERDI 2.2 Updates**

The following new feature was added:

- Added ability to add Satellite Image Layer using the [OpenTopoMap](#) as the tile provider.

The following issues were fixed:

- The error associated with layer\_sum/layer\_mean tile plots for unconventional 3D variables (#352)
- Incorrect maximum value in tile plot legend when load a configuration file with a logarithmic scale (#353)
- Unable to choose layer ranges with two or more datasets in the Dataset Panel (#356)
- Unable to choose layer ranges with two or more datasets in the Formula Panel (#356)

**PAVE or VERDI?**

How do you know if you should use PAVE or VERDI?

VERDI was developed as a replacement for the PAVE program. Because PAVE is no longer in active development and support is limited, VERDI offers the best option as a state-of-the-art visualization program.

**Latest Version: VERDI version 2.2**

**\*\*REPLACE ALL PRIOR\*\* versions of VERDI with this release version.**

[DOWNLOAD](#) | [DOCUMENTATION](#)

---

**VERDI Training**

**Support**

- [CMAS Help Desk](#)
- [CMAS Center Forum - VERDI Category](#)

---

**Previous Documentation**

1.1

---

**Online Resources**

- [A New Tool for Analyzing CMAQ Modeling Results: Visualization Environment for Rich Data Interpretation \(VERDI\)](#) - presented by Donna Schwede at the 2007 CMAS Conference.
- [Visualization Environment for Rich Data Interpretation - VERDI](#) - poster presented by Jo Ellen Brandmeyer and Elizabeth Adams at the 2016 CMAS Conference.

---

**System Requirements**

O/S	Windows, Linux, Mac
Memory	1024 MB RAM
Software	All needed VERDI components are contained in the distribution package.

---

**Partners**

- [Institute for the Environment](#)
- [CMAS Center](#)
- [U.S. EPA Atmospheric & Environmental Systems Modeling Division](#)
- [U.S. EPA Environmental Modeling and Visualization Laboratory](#)
- [General Dynamics Information Technology](#)

Figure 1: Top of VERDI Page

**VERDI 2.1.6 Updates**

Updated netCDF-Java to version 5.5.3 (<https://github.com/Unidata/netcdf-java/releases/tag/v5.5.3>)

The following new features were added:

- Visualize differences between time-independent model files (#341)
- Reading netCDF files with unconventional dimension names (#344)
- Calculate layer (sum and mean) statistics for all layers or a subset of layers chosen in the dataset panel followed by creation of a new tile plot. (#345)

The following issues were fixed:

- Incorrect values for probed grid cells for statistics "maximum 8hr mean" in tile plot (#325)
- Batch script does not turn off column/row labels and legends as specified in the configuration file (#347)

**VERDI 2.1.5 Updates**

Updated OpenJDK to version java 21.0.1 2023-10-17 LTS to fix security vulnerability.

The following new features were added:

- Open and display a MPAS Mesh File (#324)
- Documentation on how to visualize fine scale model output datafiles with GIS layers
- Support sub-domain on a Vertical Cross Section Plot from the command line (#326)

The following issues were fixed:

- Save tile plot as shapefile from GUI (#322)
- MPAS scatterplot tool from GUI (#255)
- Saving and Opening a Project (#318)
- Read zgrid variable from MPAS using VERDI CLI (#257)

The following enhancement was made (#200):

- VERDI saves color values using six digit hex color codes to a saved configuration file and reads configure files using either 32 bit integer codes or the hex color codes.

The following features were deprecated:

- Disabled Domain Window Including "Metadata Me" (#320)

**VERDI 2.1.4 Updates:**

Updated OpenJDK to version 17.0.2 to fix security vulnerability: <https://openjdk.java.net/groups/vulnerability/advisories/2021-10-19>

- Ability to display 3-D contour plot (#184, #304)
- Ability to display zgrid tile plot for MPAS dataset (#257)
- Allow user to modify scatter plot dot size (#260) Allow animate plot to be exported as .mp4 movie format (#270)
- Fix Tile Plot Legend Placement (#307)
- Allow tabbed panes that were closed to be reopened (#285)

**VERDI 2.1.3 Updates:**

Update log4j 2.17.1 to fix security vulnerability: <https://logging.apache.org/log4j/2.x/index.html>

- Note, the User Manual for VERDI has not been updated. It will be updated for the next Major Release.

**VERDI 2.1.2 Updates:**

Update log4j 2.17 to fix security vulnerability: <https://logging.apache.org/log4j/2.x/index.html>

- Fixed linux build to use openjdk 16.0.2 2021-07-20.
- Re-enabled the splash screen with automatic version numbering.
- Note, the User Manual for VERDI has not been updated. It will be updated for the next Major Release.

**VERDI 2.1.1 Updates:**

Hot Patch for VERDI with log4j 2.0.16 to remove message lookup capability to eliminate the log4shell security vulnerability: <https://logging.apache.org/log4j/2.x/security.html>

- Fixed Polar Stereographic Projection Issue for Tile Plot Display of WRF Files.

**VERDI 2.1 Updates:**

- Enhanced user interface and interactive features related to observation overlays (e.g., preview feature, custom symbols)
- Added support for setting legend levels from a batch script.
- Improved error messaging (when an observation data set does not contain data for the map being shown).
- Updated Java Runtime Environment to OpenJDK 16.02

**History of VERDI**

Driven by the air quality modeling community's need for a replacement to PAVE, the U.S. EPA sponsored the development of VERDI. PAVE is a Unix-based software system written in C and Motif. While the EPA is satisfied with the functionality of PAVE and desired to keep those capabilities, they recognize that the PAVE technology is outdated and wanted an updated, more efficient, flexible, and modular visualization software system. Argonne National Laboratory initially developed VERDI to duplicate the functionality of PAVE in a Java program. VERDI development continues thanks to the efforts of the U.S. EPA's National Computer Center/Environmental Modeling and Visualization Laboratory and the Institute for the Environment at the University of North Carolina - Chapel Hill.

Community Modeling and Analysis System (CMAS)

[More About CMAS](#) [Contact Us](#) [Privacy Policy](#)

General inquiries about the CMAS Center and questions about the web site should be directed to [cmas@unc.edu](mailto:cmas@unc.edu)

The screenshot shows the CMAS (Community Modeling and Analysis System) website. At the top, there is a search bar with 'Search for...' and a 'Search' button. To the right is a decorative graphic featuring a globe with a yellow and red heatmap overlay, and the letters 'CMAS' in large yellow font. Below the search bar is a navigation menu with links: Help, Download, Software, Conference, Training, Resources, User Details, and Log Out. A breadcrumb navigation at the bottom left shows the path: HOME / DOWNLOAD / FORMS / STEP 2. The main content area is titled 'Software Download, Step 2'. It contains three dropdown menus: 'Select the product you wish to download:' set to 'VERDI 2.2', 'What platform will this run on?' set to '--Please Make a Selection--', and 'What compiler will you use?' also set to '--Please Make a Selection--'. A blue 'Submit' button is located below these fields. At the bottom of the page, there is footer information: 'Community Modeling and Analysis System (CMAS)', links to 'More About CMAS', 'Contact Us', and 'Privacy Policy', and a note that general inquiries should be directed to cmas@unc.edu. The footer also features the UNC logo and the text 'INSTITUTE FOR THE ENVIRONMENT'.

Figure 3: Downloading VERDI from the CMAS Web Site, Step 2



The screenshot shows the CMAS (Community Modeling and Analysis System) website. At the top, there is a search bar with a placeholder "Search for..." and a "Search" button. To the right of the search bar is a decorative graphic featuring a globe with a yellow and red heatmap overlay, and the word "CMAS" in large yellow letters. Below the search bar is a navigation menu with links: Help, Download, Software, Conference, Training, Resources, User Details, and Log Out. A breadcrumb navigation bar at the bottom of the page shows the path: HOME / DOWNLOAD / SOFTWARE / VERDI / VERDI 2.2.

## VERDI 2.2

Installation instructions, documentation, and software for VERDI 2.2

**NOTE: Save the files that you download into a common directory.**

File type	Download link and file name	Release/Modified date
Documentation	<a href="#">View</a>	10/21/2024
Download for Windows	<a href="#">VERDI_2.2_win64_20250901.zip</a>	02/20/2025
Download for Linux	<a href="#">VERDI_2.2_linux64_20250901.tar.gz</a>	02/20/2025
Download for Mac OSX	<a href="#">VERDI_2.2_mac_20250901.tar.gz</a>	02/20/2025
Download Observation Overlay Data	<a href="#">Link to the Google Drive Folder</a>	10/21/2024

**Community Modeling and Analysis System (CMAS)**

[More About CMAS](#) [Contact Us](#) [Privacy Policy](#)

General inquiries about the CMAS Center and questions about the web site should be directed to [cmas@unc.edu](mailto:cmas@unc.edu)



Figure 4: Downloading VERDI from the CMAS Web Site, Step 3




Figure 5: VERDI Documentation on the CMAS Web Site

### 1.3 Where to Obtain VERDI Documentation

Documentation is available in several locations, described below. Each location provides links to the available documentation for VERDI, which can be viewed in your web browser or downloaded and saved to your computer.

- The main VERDI page has a link to Documentation.
- The VERDI download page on the CMAS website contains links to all of the available documentation.
- On the left-hand side of the [www.cmascenter.org](http://www.cmascenter.org) web site, open the drop-down menu for Help and choose Documentation. Select the documentation for VERDI from the drop-down list and click Search. Select the model release from the drop-down list and click Search. The resulting documentation pane shows that the available documentation for the chosen release of VERDI GitHub:[Figure 5](#) or PDF:[Fig- 5](#).
- To go directly to the most recent VERDI documentation click on DOCUMENTATION from the VERDI software: <http://www.cmascenter.org/verdi>. [Figure 6](#) shows the list of documentation that is available for download for VERDI 2.2.



## Documentation

The following documents are available for VERDI 2.2:

- [RELEASE NOTES](#)
- [USERS GUIDE](#)

[Search for other Model Documentation?](#)

We have also created a [Porting Guide](#) for building different CMAS software components on unsupported environments.

Due to the nature of model research and development, the model documentation may not always be up-to-date with the code. We will make every effort to provide current documentation or notices when the documentation differs from the available models.

If you wish to download any of the CMAS-supported models, please visit the [Software Download](#) page.




Figure 6: VERDI Documentation on the CMAS Web Site

## 1.4 Help Desk Support for VERDI

You are encouraged to search the new CMAS User Forum, by selecting the VERDI category: <https://forum.cmascenter.org/c/verdi> or using the old [M3USER listserv](#) for VERDI-related technical support questions; report errors and/or requests for enhancement to the m3user forum. The m3user forum is supported by the community and also by CMAS to help users resolve issues and identify and fix bugs found in supported software products.

## 1.5 Future VERDI Development

As stated in Schwede et al. (2007),[1] “VERDI is intended to be a community-based visualization tool with strong user involvement.” The VERDI source code is available to the public under a GNU Public License (GPL) license at <https://github.com/CEMPD/VERDI>. This allows users who wish to make improvements to VERDI to download the software, and to develop enhancements and improvements that they believe may be useful to the modeling community. Examples could include user-developed readers for additional file formats and modules for additional plot types. Users may wish to contribute data analysis routines, such as adding the ability to do bilinear interpolation (smoothing), or to contribute other enhancements to the existing plot types. The direction of future development will depend on the resources and the needs of the modeling community. If you are interested in contributing code to VERDI, please review the information in Chapter 14, “Contributing to VERDI Development.”

# 2 Requirements for Using VERDI

## 2.1 Java

VERDI uses OpenJDK version “21.0.1”. The OpenJDKTM is provided as part of the VERDI release for 32- and 64-bit Linux and Windows. If your computer requires a different version, see Section 3.3.

## 2.2 Memory and CPU Requirements

VERDI’s memory and CPU requirements largely depend on the size of the datasets to be visualized. Most datasets can be visualized and manipulated using 6144 megabytes of RAM, while larger datasets may need considerably more. If you are using datasets that require either more or less than 6144 MB of memory, you can change the default maximum memory setting used by VERDI:

- On Windows, edit the run.bat file that you use to launch VERDI. Look for the line that starts “set JAVACMD=” and change the value for the “Xmx” argument from the default heap size of 6144M.
- On Linux or another Unix platform, you can edit verdi.sh and replace the 6144 in –Xmx6144M with a different value; for example, -Xmx6144M will allow VERDI to access up to 6144MB (or 3GB) of RAM.

Note that slower CPUs can quickly view and animate smaller datasets, whereas larger datasets require more time. As a user opens new Tile plots or other plot types, the memory requirements increase. As the user then closes the plots, the memory is released by VERDI.

## 2.3 Requirements to Run VERDI Remotely

VERDI may be used to run on a remote compute server and have the graphics display locally on your desktop machine (Unix workstation, Mac, or PC) using the Tile Plot. Your computer needs to be configured to run X-Windows. Typically, you will connect to the remote compute server using secure shell (SSH). If you are using an X-Server and wish to generate 3-D plots using OpenGL, you need to turn on OpenGL support within the X-Server.

## 2.4 Graphics Requirements

Three-dimensional contour plots require a graphics card with OpenGL or DirectX capability. By default VERDI uses OpenGL for 3D rendering. If you would like to use DirectX instead, add the line: j3d=-Dj3d.render=d3d to the verdi.ini file.

## 2.5 Display Properties

VERDI works best on screen displays that have been set to a high or perhaps the highest screen resolution ( $1440 \times 900$  for Mac, or  $1920 \times 1080$  for Windows 11/Linux). Follow these general instructions to adjust your screen resolution on the following types of computers.

- Windows 11: Click on the Start button and select Control Panel. Select Display, then Adjust resolution. Use the drop-down boxes to select your type of display, screen resolution, etc. (it may already be set at the highest resolution by default). Select Scale and layout. Change the size of text, apps, and other items - select 100% rather than the default 150%. (the 150% setting makes the VERDI app take up the entire screen, and this results in the footer information of the Tile Plot getting cut off.) Select Display Resolution:  $1920 \times 1080$ .
- Mac: Go to Applications and double-click on System Preferences. Under Hardware select Displays and then Select  $1440 \times 900$ .
- Linux: Right-click on desktop and select Display Settings. Under Resolution select option greater than (or equal to)  $1920 \times 1080$  (16:9).

# 3 VERDI Installation Instructions

This chapter provides instructions for installing VERDI 2.2 on a variety of computer platforms. The supporting libraries required by VERDI are included in the installation, along with a version of the OpenJDK for your convenience.

VERDI 2.2 is distributed as a zip or gzip file, as appropriate, for each of the following supported platforms:

- 64-bit Windows 11
- 64-bit Linux
- Mac

If you have a different computer system, select the distribution for a computer system as close to yours as possible and proceed with the installation. Although Java is considered a write-once, run-anywhere computer language, that is not necessarily true for graphical software. Therefore, an appropriate version of some graphics libraries is included in each of the above VERDI distributions.

### 3.1 Installation Instructions for Linux and Mac

Follow these instructions to install VERDI:

1. tar -xvf VERDI\_2.2\_<linux,mac>\_.tar.gz into a location where you would like to install VERDI
2. The run script for Linux is: verdi\_2.2/verdi.sh The run script for Mac is: verdi\_2.2/verdi.command
3. Create a directory *verdi* under your home directory.
4. Create an empty text file, name it *verdi.alias* and save it in your *verdi* directory. When you look at the directory listing for this *verdi* directory, you should see the *verdi.alias* file with a length of 0.
5. Locate the file *config.properties.TEMPLATE* that is in your installation directory. Copy *config.properties.TEMPLATE* to your *verdi* directory and rename that file *config.properties* only.
6. Add the path to the verdi run script to your .cshrc or .bash\_profile so that the verdi.sh script can be found from any directory  
example .cshrc set path = (\$path /proj/ie/proj/CMAS/VERDI/VERDI\_2.2)
7. Alternatively, use alias to point to full path to verdi.sh  
alias verdi.sh /proj/ie/proj/CMAS/VERDI/VERDI\_2.2/verdi.sh  
VERDI should now run if you execute the verdi.sh executable script on linux, or executing the verdi.command script on mac.

## 3.2 Installation Instructions for Windows

To install VERDI for Windows, unzip the file to a local directory on your Windows 11 computer. NOTE: You do not need to install VERDI under a Program Files directory or in the root directory on one of your hard disk drives. Therefore, you should not need Administrator rights to install VERDI 2.2. If your system is under strict control from your Administrator, you may be able to unzip the VERDI distribution under your home directory or your documents directory; however, you may have problems if there is a space in the path to your VERDI installation directory.

If you are unable to install VERDI on your computer, please check to see whether your user account is authorized to install software. You may need to request that a user with a computer administrator account install VERDI, or provide you with an account that has permission to install software. For more information about user account types, click Start and select Control Panel and then click on the User Account icon.

After successfully installing VERDI you may need to perform the following tasks under your home directory.

1. Locate your home directory.

Your home directory is typically under csh `C: //Users//yourloginid`.

So, if your login id is *staff*, your home directory is probably `C: //Users//staff`.

2. Create a new directory *verdi* under your home directory (e.g., `C: //Users//staff//verdi`).
3. Create an empty text file, name it *verdi.alias* and save it in your *verdi* directory. When you look at the directory listing for this *verdi* directory, you should see the *verdi.alias* file with a length of 0.
4. A text file named *config.properties.TEMPLATE* was installed into your VERDI installation directory. Copy *config.properties.TEMPLATE* to your *verdi* directory and rename that file *config.properties* only.

Note that VERDI writes a log file (i.e., *verdi.log*) as-needed to your *verdi* directory. This log file should remain small. However, if you need technical support we may ask for your log file. It will be a text file named *verdi.log* located in this *verdi* directory.

Setting VERDI Preferences ——————

VERDI is configured via the *config.properties* file that you copied to your home/*verdi* directory. Edit this file to specify default directories for saving files, for placing the location of configuration files, and for saving project files. Contents of *config.properties.TEMPLATE*:

```
# This file should be put in $USER_HOME/verdi/ subdirectory
# Please use double backslash for Windows platform or slash for UNIX-like platforms
# Please uncomment the following lines and modify them to suit your local settings
```

```

# Windows example settings format
# verdi.project.home=C:// Users\yourusername\VERDI_2.2\project
# verdi.config.home=C:// Users\yourusername\VERDI_2.2\config
# Linux example settings format

verdi.project.home=../../data/project
verdi.config.home=../../data/configs
verdi.user.home=../../data/model
verdi.dataset.home=../../data/model
verdi.script.home=../../data/scripts

# file folder used as default location of HUC datasets for areal interpolation

verdi.hucData=../../data/hucRegion/

# For VERDI to access remote big netCDF data files

verdi.remote.hosts=terrae.nesc.epa.gov,vortex.rtpnc.epa.gov,garnet01.rtpnc.epa.gov
remote.file.util=/usr/local/bin/RemoteFileUtility
verdi.remote.ssh=/usr/bin/ssh

# on local machine where VERDI is running.

Used to hold temporary data file downloaded from a remote machine

verdi.temporary.dir=C:\\\\ Users\\username\\temp

```

The items in the config.properties.TEMPLATE file that is installed with VERDI are commented out. To specify default directories, uncommented these lines by removing the starting '#' sign. Example settings that are provided in the default file show how to specify the paths to these locations, depending on whether the installation is for a Windows or Linux platform. Here are how the settings are used by VERDI. Note that VERDI stores the most recently used directory for each of these functions and will go to that directory when you repeat the load or save in the same session.

- verdi.project.home: Default location from which to load and save projects
- verdi.config.home: Default location from which to load and save plot configuration files
- verdi.dataset.home: Default location from which to load datasets
- verdi.script.home: Default location from which to load and save batch scripts
- verdi.hucData: Default location where area shapefiles are located; VERDI navigates to this directory when the user selects to add a dataset in the Area pane.
- verdi.remote.hosts: Contains a list of machines that the user can select to browse when adding a remote dataset using VERDI's Remote File Access capability
- verdi.remote.util: Location of the RemoteFileUtility script for Linux and Mac installations of VERDI.

Starting in VERDI version 1.4, the ui.properties file was removed and the user-configurable settings, such as the default directory locations, were moved to the config.properties file.

## 4 Starting VERDI and Getting Your Data into VERDI

### 4.1 Starting VERDI

#### 4.1.1 Windows

If you have previously configured this VERDI installation, use Windows Explorer to navigate to your installation directory. Double-click on the file **run.bat** to start VERDI. Alternatively, you can open a command window. If you do not have a shortcut to launch a command window, press the Start button and type **cmd** in the *Search programs and files* textbox. If your window is too small, go to the window's title bar and right-click; select Properties and then Layout and change your Screen Buffer Size and your Window Size appropriately.

Next, navigate to where you installed VERDI on your computer. You see the **run.bat** file. Its contents are shown in PDF:(Fig- 7) or GitHub:[Figure 7](#). If you have previously executed this VERDI installation, just type **run** and press the **Enter** key. Otherwise, you may need to customize some of the settings in this file for your configuration. If so, edit your run.bat in a text editor such as Notepad.

VERDI\_HOME needs to point to the directory where VERDI is installed, which is also the directory containing the run.bat file. In this figure VERDI is installed in the directory C:\VERDI\VERDI\_2.2.

JAVADIR needs to point to the directory where your JRE is installed. In this figure JRE is installed in the jre directory under the VERDI\_HOME directory. If you are using a JRE in a different location on your computer, change the path in your run.bat file.

All other locations are specified relative to the VERDI\_HOME or the JAVADIR, so you should not need to change any of those.


#### 4.1.2 Linux and Other Non-Windows JRE Supported System Configurations

To start VERDI from Linux and other non-Windows JRE Supported System Configurations, find the directory where VERDI was installed; then run the verdi.sh script with *sh verdi.sh* command.

On a Mac go to the /Applications/verdi\_2.2 directory and run the verdi.command script. If you have set up the path environment variable on your .cshrc or .bash\_profile or set up an alias to specify the full path, then you can run VERDI from any directory.

### 4.2 Main Window

When VERDI starts it displays its title screen as it loads. The main window is then displayed PDF:(Fig- 8) or Github:[\(Figure 8\)](#). The top of the main window contains a menu bar with the main window options (**File**, **Plots**, **Window**, and **Help**). Below the menu bar are three icons that are shortcuts to some of the



```

run.bat - Notepad
File Edit Format View Help
@ECHO OFF
SET BATCHFILE=%~f2
REM Instructions: If your USER_HOME directory is not already set,
REM you can set it here (set USER_HOME=C:\Users\myUserName).
REM Your VERDI log file will be written in the verdi subdirectory.
REM Refer to your VERDI User's Guide for more information.
SET USER_HOME=%USERPROFILE%
set VERDI_USER=c:\users\ellenjo
REM Instructions: Set the following path to the location where you installed VERDI.
SET VERDI_HOME=C:\\\\VERDI\\\\VERDI_1.6\\alpha
REM Change the following path if you are not using the version of Java installed with VERDI
set JAVADIR=%VERDI_HOME%\\jre\\1.7.0
REM Do not edit below this line
REM *****
CD .\\plugins\\bootstrap
SET JAVA=%JAVADIR%\\bin\\java
set CLASSPATH=%JAVADIR%\\bin\\;%JAVADIR%\\lib\\*;%VERDI_HOME%\\plugins\\bootstrap\\bootstrap.jar;%VERDI_HOME%\\plugins\\bootstrap\\lib\\*;%VERDI_HOME%\\plugins\\bootstrap\\lib\\*;%VERDI_HOME%\\plugins\\core\\lib\\*
REM set PATH based on 32/64 windows
set bit64=n
if /I %Processor_Architecture%==AMD64 set bit64=y
if /I "%PROCESSOR_ARCHITEW6432%"=="AMD64" set bit64=y
if %bit64%==y GOTO proc64
set PATH=%PATH%;%VERDI_HOME%\\plugins\\core\\lib\\win32
REM echo set to win32 path
GOTO proc32
:proc64
set PATH=%PATH%;%VERDI_HOME%\\plugins\\core\\lib\\win64
REM echo set to win64 path
:proc32
REM path has been reset for DLLs; continue
set JAVACMD=%JAVA% -Xmx1024M -classpath %CLASSPATH% saf.core.runtime.Boot
IF "%1" == "-b" GOTO scripting
IF "%1" == "-batch" GOTO scripting
%JAVACMD% %
GOTO end
:scripting
%JAVACMD% %1 %BATCHFILE%
:end
CD ..\\..\\

```

Figure 7: Starting VERDI in Windows




Figure 8: VERDI Main Window

options available in the Main Window Menu Bar; the first is an **Open Project** icon, the second is a **Save Project** icon, the third is an icon that allows you to **Undock All Plots**. These shortcuts and the options available in the Main Window Menu Bar are discussed further in Chapter 5, “Navigating VERDI’s Main Menu Options.”

To the right of these three shortcut icons are buttons that list all of the available plot types. The **Selected Formula** is displayed on the far right. The Selected Formula refers to the formula that has been selected in the **Formula** pane (discussed briefly below and in detail in Chapter 7) and that will be used to create plots.

Below the icons and plot buttons, the VERDI window is divided into two main areas: a parameters area consisting of tabbed panes on the left side and a plots area on the right side. You can resize the entire window with your mouse. You can also resize the tabbed pane separately from the plot area by placing your mouse over the dividing line between them and then moving it to the left or the right. If you want, you can separate the tabbed pane into 3 panes by using your mouse to hold onto the pane’s title bar and then move it slightly out of alignment. To reassemble the 3 panes into a tabbed pane, use your mouse to hold onto the title bar of one pane, drag it until its outline fills the outline of another pane, and then release the mouse.

The parameters area contains three tabbed panes:

- The **Datasets** pane is used to load in the dataset files that you want to work with in this session (see Chapter 6). Once the datasets are loaded, VERDI automatically displays the lists of variables that are in the datasets. To see the variables in a dataset, click on the dataset, and the variables will be displayed in the **Variables** panel underneath the list of datasets. Double-click on the

name of a variable listed on the variables panel to add it as a formula on the **Formula** pane; it also will be displayed as Selected Formula in the top right corner of the main VERDI window and will be the default formula for new plots that are created.

- The **Formulas** pane is used to create a formula that refers to the variable and the dataset that you are interested in plotting (see Chapter 7). All plots in VERDI are generated from formulas. A formula can be as simple as a single variable from one dataset or it can be an equation that uses variables from one or more datasets.
- Use the **Areas** pane to load area files for creating areal interpolation plots (see Chapter 8). An area file is defined as a shapefile that contains polygon features such as watersheds, counties, or any other set of closed polygons.

Any plots that are created are shown in the plots area on the right-hand side of the main window. These plots can be placed into their own movable windows using Plots>Undock all Plots on VERDI’s main menu, as discussed in Section 5.2.1. The Tile Plot has an option (Plot>Add Overlay> Vectors) to create a Tile Plot of a variable with a vector overlay of wind vectors or other vector types. The Vector Plot has now been removed because the Tile Plot with vector overlay is superior. The functions that are currently enabled for Tile Plots are described in Section 10.1.

### 4.3 Rearrange the Datasets, Formulas, and Areas Panes

You can rearrange the **Datasets**, **Formulas**, and **Areas** panes to be most efficient for your current work. VERDI supports resizing the entire VERDI window, floating one or more panes to other locations on your desktop, and rearranging the panes within the VERDI window.

The **Datasets**, **Formulas**, and **Areas** panes can each be configured to float so you can position them elsewhere on your desktop. To allow a pane to float, click the icon at the top of the pane that looks like a rectangle with an angle bracket above the upper-right corner; its tool tip is “Externalize this view into a floating window”. You can then click on the pane and drag it independently of the VERDI main window. For example, this is useful when you are entering a formula in the **Formulas** pane and need to refer to the variables that are in a loaded dataset. Once a pane is disconnected from the frame, the icon changes to be a box with an arrow pointing inward, with the tool tip: “Connects this panel with the frame”. Click on the box with the inward arrow to reconnect the panel with the frame. This will return the floating pane back to where it was last connected within the main VERDI window.

You can rearrange the panes within the main VERDI window. Click on the tab at the bottom of a frame and slide it along that area to change the order of the frames. Or slide it up or down and arrange the frames vertically so you can see more than one at a time. You can also click and hold a tab to slide its pane next to the other panes, consuming space that had been used by the charts pane. If you have the three panes beside each other – or two panes with tabs next to the third pane – you can easily change their relative position. Click on the title of the frame that you want to move, drag it, and then release it.

You can also change the amount of the entire VERDI window that is devoted to the 3 panes on the left vs. the charts pane on the right. Position your cursor along the line dividing these two sets of panes

such that the cursor becomes a horizontal arrow pointing both left and right. Drag the cursor to the left to reduce the size of these panes and increase the size of the chart pane, or to the right for the opposite effect.

## 5 Navigating VERDI's Main Menu Options

**Table 5-1** lists the main menu options that are available on the top menu bar in VERDI's main window (see [Table 5-1](#)). These options are discussed in detail below.

Table 5-1. VERDI Main Menu Options

File	Plots	Window	Help
Open Project	Undock All Plots	Areas	VERDI Help
Save Project	Animate Tile Plots	Datasets	About
Save Project As			Formulas
View Script Editor			
Exit			

### 5.1 File Menu Options

#### 5.1.1 Open Project

**Open Project** retrieves projects that were saved during a previous session (using the two **Save Project** options described in Section 5.1.2). Note that when you use a saved project, *it is very important* to load that project into VERDI *before* you load any additional datasets or create any additional variables/formulas. If you have already loaded datasets and then try to open a previously saved project, VERDI will show you a message that says “All currently loaded datasets will be unloaded” and will ask if you want to continue.

#### 5.1.2 Save Project

The **Save Project** and **Save Project As** options save dataset lists and associated formulas as a “project” for later use.

Note that plots are not saved with a project; only datasets and formulas are saved. If you wish to save a plot configuration for later use, see Chapter 11 section on Saving Plot Configurations ([Chapter 11](#)).

#### 5.1.3 View Script Editor

Use the **View Script Editor** to modify and run batch scripts within VERDI. Several sample script files are provided with the VERDI distribution under the \$VERDI\_HOME/data/scripts directory. Use the Open popup window to specify file\_patterns.txt, which is one of the sample script files. The contents

of the file \_patterns.txt will be displayed in the Script Editor in the right side of the VERDI window. Modify it to specify the local directory path name for the sample data files, the formulas, the type of plots, and the image format. The plots are not rendered within VERDI, but may be viewed using an image viewer. The batch scripting language is described in the sample script files, and is described in more detail in [Chapter 17 VERDI Batch Script Editor](#)

## 5.2 Plots Menu Options

VERDI opens a single pane for plots, to the right of the **Dataset**, **Formula**, and **Area** tabbed pane. Each plot is created in its own pane and is placed in the plot pane. The most recent plot is displayed on the top. Each plot has a tab beneath it listing the type of plot and the formula used to create it. If you want to view a previously created plot, select the tab associated with its pane underneath the current plot; the selected plot is then displayed on top.

### 5.2.1 Undock All Plots

As with the **Dataset**, **Formula**, and **Area** panes (Section 4.3), plot panes can be undocked or externalized so that you can move them into separate, floating windows. This allows side-by-side comparisons of plots. Note that undocking is performed only on previously created plots; each plot is placed within the VERDI main window when it is generated.

### 5.2.2 Animate Tile Plots

This option opens an **Animate Plots** dialog box PDF:(Fig- 9)) or GitHub:([Figure 9](#)) that allows you to select one or more plots, select a subset of the time range, and create an animated GIF file. There is also a separate way to create a QuickTime movie instead of a GIF, if desired.

Within the **Animate Plots** dialog box, you can **select plot(s)** to animate by clicking the check box beside each plot name.

You can choose to animate a single plot, or animate multiple plots synchronously. To view multiple animated plots synchronously, undock the plots (see Section 5.2.1) and arrange them so that they are located side by side for visual comparison during the animation. NOTE: The underlying number of time steps must match or the Start button will not activate (PDF:(Fig- 9)) or GitHub: [Figure 9](#)).

After selecting your plots, **select the time range** by specifying both the **starting time step** and **ending time step** of the animation. The selected plots animate together over the selected time interval. If the plots do not cover the same time range, the start button will be greyed out.

To create an animated GIF, check the **Make Animated GIF(s)** option in the **Animate Plots** dialog box. In the **Save** dialog box that appears, select the directory in which to store the file and the name to use for the animated GIF, then click the save button. When saving as an animated GIF, when multiple plots are selected, each animated plot will be saved to a separate animated GIF file. For example, if three plots were selected, the animated plots would be saved as <filename>-1.gif, <filename>-2.gif, <filename>-3.gif. You can view the animated GIF by opening the file in a web browser. see (PDF:(Fig- 10)) or GitHub: [Figure 10](#)




Figure 9: Side-by-side display of Tile Plots with Animate Plots Menu Dialog Box

Creating a QuickTime movie is also an option, but this is not done through the **Plots>Animate Tile Plots** main menu option. Instead, use the **Plot** menu option found at the top of each individual plot to make a QuickTime movie.

### 5.3 Window Menu Options

The **Window** menu provides an alternate way to select windows/panes to be brought to the front, and provides the same function as clicking on the tabs at the bottom of the windows/panes.

#### 5.3.1 Datasets, Areas, and Formulas

Select from the **Window** pull-down menu to bring to the front either the **Datasets** pane, **Areas** pane, or **Formulas** pane when those panes are docked.

#### 5.3.2 Script Editor

This option appears in the Window menu if you have a script editor window open. You can select this menu item instead of pressing the Script Editor tab at the bottom of its pane.




Figure 10: Animate Plots Dialog and Tile Plots

### 5.3.3 List of Plots

The **Window** pull-down menu is automatically updated each time a plot is created or removed in a VERDI session; each entry in the plot list indicates the type of plot and the formula used (e.g., Tile O3[1]). A check mark to the left of a plot designates the active plot. Click on a plot entry to bring that plot to the front for viewing. Alternatively, you can bring a plot to the front by selecting the desired **plot tab** underneath the plots area of the main window or by clicking on the plot's window for undocked plots. As in the menu entries, each **plot tab** is labeled with the plot type and the formula used.

## 5.4 Help Menu Options

The **Help** pull-down menu contains two items that you can use to learn more about VERDI. When you select **VERDI Help Documents**, you can select to view either the user manual or the developer instruction in your PDF-compatible reader. When you select **About** a popup window that contains the name of the product, the version number, and the date the software was built is displayed.

# 6 Working with Gridded Datasets

## 6.1 Gridded Input File Formats

### 6.1.1 Model File Format Conventions

VERDI currently supports visualizing files in the following file format conventions: CMAQ Models-3 Input/Output Applications Programming Interface (I/O API) netCDF, WRF netCDF, CAMx (UAM-IV), MPAS netCDF, and ASCII format (for observational data). VERDI uses a customized version of the thredds/NetCDF Java library v5.5.3 (<http://www.unidata.ucar.edu/software/netcdf-java>).

The CMAQ Models-3 I/O API was designed as a high-level interface on top of the netCDF Java library. (see <https://www.cmascenter.org/ioapi/> and <http://www.unidata.ucar.edu/software/netcdf/> for further information). The Models-3 I/O API library provides a comprehensive programming interface to files for the air quality model developer and model-related tool developer, in both FORTRAN and C/C++. Models-3 I/O API files are self-describing and include projection information within the gridded dataset. See Chapter 12 for additional information on what projections and gridded data file format conventions are currently supported by VERDI.

NetCDF and Models-3 I/O API files are portable across computing platforms. This means that these files can be read regardless of what computer type or operating system you are using. Routines are available to convert data to these formats or new code can be written and contributed to VERDI for use by the community. Discussion of the Models-3 I/O API conversion programs and how to use them can be found in Chapter 13, “Models-3 I/O API Utilities, Data Conversion Programs, and Libraries”. If you write a routine for VERDI to read gridded data from other formats, please consider contributing your code to the user community using GitHub, as described in Chapter 14.

### 6.1.2 Observational Data Formats

VERDI can use observational data in either using ASCII file or created using Models-3 I/O API. An ASCII file needs to have data in tab-separated columns. The first four columns need to be in the order shown in PDF:(Fig- 11)) or GitHub:[Figure 11](#). VERDI allows the user to specify an alphanumeric value (either numbers and/or letters) for the fourth column (Station ID). One or more additional columns must have the header format ‘name(units)’. Spreadsheet programs can be used to edit and write the files by choosing ASCII output; be certain to designate **tab** as the delimiting character (instead of comma). Data within a column must be complete, because empty fields prevent VERDI from reading the observational data.

Observational data in ASCII format can be obtained from many data sources. Data can be downloaded from the CMAS Center Google Drive

[https://drive.google.com/drive/u/1/folders/1YIcmYtPH\\_DRyN51dDEQDh3r5Q\\_4iNLuu](https://drive.google.com/drive/u/1/folders/1YIcmYtPH_DRyN51dDEQDh3r5Q_4iNLuu)

or the CMAS Center Data Warehouse on AWS

[https://https://cmas-amet.s3.amazonaws.com/index.html#AMET/obs\\_overlay/](https://https://cmas-amet.s3.amazonaws.com/index.html#AMET/obs_overlay/)

or EPA’s Remote Sensing Information Gateway - RSIG

<https://www.epa.gov/hesc/remote-sensing-information-gateway>

To use a consistent set of units for the model data and the observational data, you may need to import the ASCII data into a tool (e.g., a spreadsheet or database program) and perform a unit conversion.

Timestamp (UTC)	LONGITUDE (deg)	LATITUDE (deg)	STATION (-)	pm25 (ug/m3)
2005-08-26T00:00:00-0000	-121.7842	37.6875	060010007	11.0000
2005-08-26T00:00:00-0000	-122.3991	37.7660	060750005	12.0000
2005-08-26T00:00:00-0000	-122.2034	37.4829	060811001	21.0000
2005-08-26T00:00:00-0000	-121.8950	37.3485	060850005	16.0000
2005-08-26T01:00:00-0000	-121.7842	37.6875	060010007	21.0000
2005-08-26T01:00:00-0000	-122.3991	37.7660	060750005	22.0000
2005-08-26T01:00:00-0000	-122.2034	37.4829	060811001	19.0000
2005-08-26T01:00:00-0000	-121.8950	37.3485	060850005	20.0000
2005-08-26T02:00:00-0000	-121.7842	37.6875	060010007	28.0000

Figure 11: Example observational data file showing format

VERDI doesn't allow the user to use an observational variable to create a formula, so conversions to different units must be performed before loading the data into VERDI.

Alternatively, you can use a converter such as AIRS2M3 (see Chapter 13) to convert ASCII observational data into Models-3 I/O API “observational-data” files.

## 6.2 Example Datasets

Several example datasets are provided under the \$VERDI\_HOME/data directory. For example:

- Windows: %VERDI\_HOME%\data
- Mac: \$VERDI\_HOME/data/
- Linux: \${VERDI\_HOME}/data

These datasets may be used to recreate example plots that are provided in this user's manual, including a tile plot with observational data overlay (see Section 11.6.3.1) and example datasets for the various projections that VERDI supports including Lambert Conformal Conic (LCC), polar stereographic, Universal Transverse Mercator (UTM), and Mercator. The data directory currently contains seven subdirectories:

1. CAMx – contains sample CAMx dataset and camxproj.txt file
2. configs – contains sample config and theme files
3. hucRegion – contains Hydrologic Unit Code (HUC) shapefiles for region 3 (southeast US)
4. model – contains sample WRF netCDF, MPAS netCDF, and CMAQ Models-3 I/O API datasets
5. obs – contains an ASCII formatted observational dataset (Section 6.1.2), and an observational dataset created by airs2m3 converter (Chapter 13).
6. plots – contains sample plots created by VERDI
7. scripts – contains sample batch scripts




Figure 12: Open Dataset File Browser

### 6.3 Adding and Removing a Dataset from a Local File System

To load a data set from a local file system, press the yellow **plus** button at the top of the **Datasets** pane. A file browser PDF:(Fig- 12)) or GitHub:(Figure 12) allows you to select a dataset for use in VERDI. Support for loading data from a remote file system was added beginning in version 1.4. The use of the yellow **plus remote** button will be discussed in Section 6.4.

After you select a dataset, VERDI loads header information and displays the available variables, time steps, layers, and domain used by the file in the **Datasets** pane PDF:(Fig- 13)) or GitHub:(Figure 13). (The actual model data are not loaded until later, when plots are created.) To view the variables for a particular dataset that has been loaded, click on the dataset name in the list to highlight it, and the variables will be listed in the panel below.

Datasets can be removed by highlighting the name of the dataset in the dataset list and pressing the yellow **minus** button. Note that although the dataset will be removed, the number that was assigned to that dataset will not be reused by VERDI during the current session (unless there had been only one dataset loaded, and it was removed; in that case the next dataset that is loaded will be labeled number 1).




Figure 13: Datasets Pane Displaying Information about a Dataset

## 6.4 Adding and Removing a Dataset from a Remote File System

Remote File Access allows VERDI to access NetCDF data sets that are located on other machines included in the verdi.remote.hosts settings using SSH. To enable remote support, the RemoteFileUtility and ncvariable utilities within RemoteFileReader.tgz must be installed with execute permission on the machine where the remote files are located. Verdi expects those files to be located in /usr/local/lib but that can be customized through the remote.file.util setting in the config.properties file in the user's home/verdi directory on the local machine.

VERDI provides users with the ability to select and add variables from datasets on remote file systems. To do this, press the yellow **plus remote** (plus with a diagonal arrow) button at the top of the **Datasets** pane. In the Remote File Access Browser PDF:(Fig- 14)) or GitHub:(Figure 14) that appears, enter your user name, choose a host from the list, and enter your password, then click **Connect**.

Figure 14. Available Hosts in the Remote File Access Browser

### 6.4.1 Remote File Browser

The top panel displays a listing of the home directory on the remote file system, as shown in PDF:(Fig- 15)) or GitHub:(Figure 15). The current path is displayed in the text box and users can edit this information to change to another directory. An alternate way to navigate between directories is using the middle panel. In the middle panel, double click on a directory name to go into that directory, or click on the “..” at the top of the middle panel to navigate up a directory. As you enter a directory, the contents of the directory will be displayed as a list in the middle panel. Directory names are followed by a “/” symbol, while filenames do not have a “/” symbol after them. View the variables within each file of interest by double clicking on the netCDF filename listed in the middle panel. NOTE: if the selected file has a format that is not supported by VERDI then the following message will be displayed in the bottom panel: “Not a valid NetCDF file”. For supported netCDF files, VERDI will provide a list of variables that are available within the file in the bottom panel labeled “Select one or more variables”. To select variables from the list, use your mouse to click on a single variable, or use either the Shift key with the mouse to select a contiguous list of variables, or the Control key with the mouse to select a set of individual variables. Once the variables that you would like VERDI to read are highlighted, click on the **Read** button.

The variables read from the remote dataset will be displayed in the dataset and variable browser in the same way that variables from a local dataset are added and displayed within VERDI. The subsetted local dataset names are identical to the file names on the remote host, except for an additional extension that enumerates how many times the remote files were read and saved locally by VERDI (i.e., filename1, filename2, filename3, etc.), as shown in PDF:(Fig- 16)) GitHub:Figure 16. To add variables from the same remote dataset, click on the **plus remote** button, and repeat the above procedure.

The Remote File Browser retains the login session and the directory that was last accessed by the user to facilitate ease of accessing remote datasets. VERDI increments the numerical extension to the dataset name to indicate that this subset file was created using the same remote dataset, but that the subset file with the new numerical extension may contain a different subset of variables. Note that VERDI does not check to see if the same variable from the same remote dataset has already been read. Also, subset files read in by VERDI are saved either to your home directory on your local file




Figure 14: Available Hosts in the Remote File Access Browser




Figure 15: Select One or More Variables from Remote Dataset

system (e.g., C:\ Users\username on a Windows 7 computer), or to the location that is specified in the config.properties file using the verdi.temporary.dir setting. Refer to Section 6.4.2 on how to edit and save the config.properties file.

The files are saved on your local machine to facilitate project management. To be able to save and then load a project for future use, the files need to be saved on the local machine. To avoid filling up your local file system, regularly inspect the file list in the home or verdi.temporary.dir directory and manually delete unneeded subset files.

Remote datasets can be removed from the dataset list in VERDI using the same procedure as for removing local datasets: highlight the name of the dataset in the dataset list and press the yellow **minus** button. Note that although the dataset will be removed from the dataset list, the number that was assigned to that dataset will not be reused by VERDI during the current session.

#### 6.4.2 Adding Additional Remote Hosts

VERDI contains the RemoteFileUtility and ncvariable programs that enable VERDI to add your Models-3 I/O API netCDF or WRF netCDF dataset from a remote file system. A gzipped tar file is available in the \$VERDI\_HOME directory.

1. The RemoteFileUtility c-shell script and ncvariable binary need to be installed with execute permission on the machine where the remote files are located either in /usr/local/bin by the System Administrator, or you can place it in a different location on the remote machine and specify that location in the configure.properties file located in your \$USER\_HOME/verdi/ directory (see section 3.4 for the specific directory location that is used for each platform [Linux, Windows, Mac]). A template for the configure.properties file called configure.properties.TEMPLATE is provided in the distribution under the \$VERDI\_HOME directory.
2. A README file provided with the software contains instructions on how to compile the source code if the binaries provided do not match your operating system.
3. Copy the file configure.properties.TEMPLATE to configure.properties. Edit the configure.properties file in the \$USER\_HOME/verdi directory. Add the name or IP address of the Linux server, preceded by a comma, at the end of the list of machines defined as remote hosts in the configure.properties file, as shown in PDF:(Fig- 17)) or GitHub:[Figure 17](#). You then need to restart VERDI in order for it to recognize a newly added remote host name.

## 6.5 Variables List

The variables list shows all of the variables contained in a loaded dataset see PDF:(Fig- 18)) or GitHub:[Figure 18](#). To display a variables list, select the name of the dataset of interest in the **Datasets** pane. Each of the variables in the list can be used to create a formula in the **Formula** pane that can then be used to create plots. VERDI allows the user to automatically add a formula by double-clicking on the name of a variable. This automatically creates a formula that contains the variable for the





Figure 16: Remote Dataset Labeled with Number at End of the Filename



```

# This file should be put in $USER_HOME/verdi/ subdirectory
# Please use double backslash for Windows platform or slash for UNIX-like platforms
# Please uncomment the following lines and modify them to suit your local settings

# Windows example settings format
# verdi.project.home=C:\\\\Users\\\\yourusername\\\\VERDI_2.2\\\\project

# Linux example settings format
#
verdi.project.home=../../data/project
verdi.config.home=../../data/configs
verdi.dataset.home=../../data/model
verdi.script.home=../../data/scripts

# Watershed Deposition Tool (WDT) default area file folder
#           used as default location of HUC (area) datasets
verdi.hucData=../../data/hucRegion/

# For VERDI to access remote, big NetCDF files
verdi.remote.hosts=sycamore.unc.edu
remote.file.util=/Users/lizadams/Downloads/VERDI_2.2/remote_read/RemoteFileUtility
verdi.remote.ssh=/usr/bin/ssh

# on local machine where VERDI is running. Used to hold temporary data file downloaded from a remote machine
verdi.temporary.dir=C:\\\\temp

~
~
~
~

```

Figure 17: Edit configure.properties File to Add a Remote Host

loaded dataset and makes it the default formula for making plots. In addition, you may right-click on the name of the variable to show a popup menu as shown in the middle of the figure. From this menu you can either add the variable as a formula, or you can add it into the formula editor so that it can be used to compose more complex formulas. Formulas are described in more detail in Chapter 7.

## 6.6 Time Steps and Layers Panels

The range that is available for the dataset is listed in the Time Steps or Layers Panel in parenthesis next to the label for the panel. PDF:(Fig- 18)) or GitHub:[Figure 18](#) shows that the dataset has 25 time steps with the range displayed as: Time Steps (1-25). You can use a subset of the full time step range by clicking on the Use Time Range checkbox, and then using the Min and Max spinner controls to set a new minimum or maximum value, for example choosing time step 2 as the minimum time step and time step 4 as the maximum. When a tile plot is created, it will only display time steps 2-4. Detailed instructions for using the **Time Steps** and **Layers** panels are discussed in Chapter 9, “Subsetting Spatial and Temporal Data.”

## 6.7 Saving Projects

As noted in Section 5.1.2, lists of datasets and formulas can be saved as “projects” using the Save Project option in the **File** pull-down menu on the VERDI main window. Refer back to that section for




Figure 18: Right-Click on Variable in Dataset Pane

discussion on saving new projects and loading existing projects. Note that the plots created in VERDI are not saved with the project.

## 7 Working with Formulas

All plots in VERDI are generated from formulas. A formula is used to compare or manipulate variables in one or more gridded datasets. A formula can be as simple as a single variable from one gridded dataset or it can be an equation that uses variable(s) from one or more gridded datasets. Formulas are used to create visualizations that can assist with model performance evaluations, for example, or can help in comparing model results with observations.

### 7.1 Adding and Removing a Formula

After loading the desired gridded datasets, you can use the variables in them to create formulas. To use a variable to create a simple formula, double click on the name of the variable. This will add the formula <Variable Name>[<Dataset Number>] to the formula list in the **Formulas** pane—for example, O3[1]. To add a variable to the formula editor window, highlight the variable, **right click** on the variable name in the **Datasets** pane, and select **Add Variable(s) to Formula Editor**. To add all or a subset of variables from the **Dataset** pane to the formula editor window, click on the first variable to highlight it, hold the Shift key down and click at the last variable that you want to include, then right click and select **Add Variables(s)**. The formulas that are highlighted using this method will be added to the formula editor PDF:(Fig- 19)) or GitHub:(Figure 19).

After the variable names are added to the Formula Editor, click on the formula pane and use the cursor and the keyboard to type in the mathematical functions and operators where needed to create a valid formula (see Section 7.2 and Chapter 16). After the formula has been created in the Formula Editor, click the **Add** button to place it in the list of formulas available in the **Formula** pane.

To remove a formula from the formulas list, highlight the name in the list and press the square-shaped button on the top-left corner with a tooltip saying “Delete formula”. Note that removing a formula from the formula list does not remove plots that were created prior to the deletion of the formula.

### 7.2 Example Formulas

To examine the values of ozone in dataset 1, the formula would be “O3[1]”.

To examine the difference in ozone between datasets 1 and 2, the formula would be “O3[1]-O3[2]”.

To calculate the percent difference in ozone between datasets 1 and 2, the formula would be “(O3[1]-O3[2])100/(O3[2])”. *To identify all cells where the ozone concentration exceeds a certain value, you can use the Boolean operators to focus on ranges of your data that are of particular interest. A Boolean expression will evaluate to either True = 1 or False = 0. For example, to plot the cells in which the ozone values in dataset 1 exceed 0.080 ppm, you could use the formula*




Figure 19: Adding Multiple Variables to Formula Editor

$“(O3[1]>0.080)O3[1]”$ . In the resulting plot, each cell where O3[1] exceeds 0.080 will show the value of O3[1] for that cell; for all other cells the value shown will be zero.

The notations that can be used in formulas to represent various mathematical functions, and the order of precedence of these functions, are listed in Chapter 16, “Mathematical Functions.”

### 7.3 Selecting a Formula for Plotting

You must select a formula before creating a plot. Check to see which formula is highlighted in the **Formula** pane, or look to the right of the plot buttons above the plots area of the main window to see the selected formula. By default, VERDI designates the most recently added formula as the selected formula. To change the selected formula to a different one in the list, click on a formula in the list on the **Formulas** pane, and you will then see it displayed as the selected formula above the plots area.

### 7.4 Saving Formulas

Both formulas and datasets can be saved using the **Save Project** item in the **File** pull-down menu on the VERDI main window. Saving new projects and loading existing projects were discussed in Section 5.1.

### 7.5 Time Step and Layer Ranges

Instructions for using the **Time Steps** and **Layers** panels are discussed in Chapter 9 Subsetting Spatial and Temporal Data.

## 8 Working with Area Files

### 8.1 Area File Formats

Area files are defined in VERDI as shapefiles that contain area features such as watersheds and counties, or any other shapefile that consists of a set of closed polygons.

The shapefile format (ESRI, 1998) consists of four files.

1. The \*.shp file contains the actual shape vertices.
2. The \*.shx file contains the index data pointing to the structures in the .shp file.
3. The \*.dbf file contains the attributes (e.g., unique county ID).
4. The \*.prj file contains the map projection information associated with the polygons.

## 8.2 Example Area File

Shapefiles that contain closed polygons are used by VERDI to interpolate gridded data to geographic boundary regions to create Areal Interpolation Plots. Shapefiles containing state, county, or census block, for example, or any other shapefile containing polygon areas may be used in VERDI to calculate and map formulas to the user-selected geographic regions. An example shapefile containing the 8-digit HUC watershed boundary map for the Southeast (HUC 3) is provided in the VERDI release under the \$VERDI\_HOME/data/HucRegion directory.

Examples of on-line data archives for these shapefiles include:

<http://datagateway.ncrs.usda.gov>

<https://www.census.gov/geographies/mapping-files.html>

## 8.3 Requirements for Shapefiles used in Areal Interpolation

In previous versions there was a requirement for Shapefiles used for areal interpolation to use units of degrees (not meters) and should use the following datum: DATUM[“unknown”, SPHEROID[“SPHERE”, 6370000.0, 0.0], TOWGS84[0,0,0] This is no longer the case, the shapefile will be read into VERDI using the projection information that comes with the shapefile. This was tested using the USA States shapefile from the Census Bureau: cb\_2019\_us\_state\_500k which uses the following projection string:

GEOGCS[“GCS\_North\_American\_1983”,DATUM[“D\_North\_American\_1983”,SPHEROID[“GRS\_1980”, 6378137,298.257222101]],PRIMEM[“Greenwich”,0],UNIT[“Degree”,0.017453292519943295]]

## 8.4 Adding and Removing an Area File

To load a shapefile, press the yellow **plus** button at the top left corner of the **Areas** pane PDF:(Fig- 20)) or GitHub:[Figure 20](#). A file browser PDF:(Fig- 21)) or GitHub:[Figure 21](#) allows you to change directories and select a shapefile file for use in VERDI. Click on the shapefile name and click **Next**. The **Open Area** popup window is displayed next, allowing you to select the name of the field to read from the file. Use the pull-down menu and click on the Name Field PDF:(Fig- 22)) or GitHub:[Figure 22](#) to be used. Each shapefile has a projection file associated with it (e.g., myFile.shp also has myFile.prj). After specifying the Name Field, select **Finish**. The resulting plot will be in the same projection as the gridded information used in the plot.

## 8.5 Areas List

The shapefile name(s) are listed in the top panel of the **Areas** pane, and the name fields for the polygons provided in the shapefile(s) are listed in the panel underneath PDF:(Fig- 23)) or GitHub:[Figure 23](#). The actual model data are not loaded until the Areal Interpolation plots are created. As additional shapefiles are added, the name fields associated with each shapefile are appended to the bottom of the Areas list. Use the scrollbar on the right side of the **Areas** pane to view the additional name fields that are available.

To remove a shapefile, click on the name of the shapefile and press the yellow **minus** button at the top left corner of the **Areas** pane.

## 8.6 Areal Interpolation

When you select the Areal Interpolation Plot, your selected formula is remapped over the polygon areas that are listed in the **Areas** pane. To select a subset of the polygon areas, and view the average and total values for selected formulas, see Section 10.2: Areal Interpolation Plot.

# 9 Subsetting Spatial and Temporal Data

Both the **Dataset** pane and the **Formula** pane include the three panels discussed in Sections 9.1 through 9.3: **Time Steps**, **Layers**, and **Domain**, respectively. Section 9.4 then discusses the precedence rules for subsetting data that determine whether **Datasets** or **Formulas** take priority.

## 9.1 Specify Time Step Range

The **Time Steps** panel PDF:[Fig- 24](#) or GitHub:([Figure 24](#)) displays the range of time steps included in a dataset. The maximum time-step range that can be used for a dataset or formula is specified in the **Min** and **Max** spinner controls. You can use these controls to select a subset of the available time-step range for plotting. Check the **Use Time Range** box above the spinner controls to tell VERDI to use the time-step range values you have specified when it creates a plot. By default, a plot initially displays data for the minimum time step specified in the **Time Steps** panel. The range of time steps shown in the **Time Step** spinner control at the top of the plot reflects the subset of time steps specified when the **Use Time Range** box is checked. The date and time of the time step displayed in the plot are shown below the x-axis labels. Subsetting a dataset's or formula's time-step range affect plots produced with those data. Section 9.4 describes the precedence rules.

## 9.2 Specify Layer Range

Information on the range of vertical model layers included in a dataset is displayed in the **Layers** panel PDF:[Fig- 25](#) or GitHub:([Figure 25](#)) . Use the **Min** and **Max** spinner controls to select a subset of the available layer data for plotting. Check the **Use Layer Range** box above the spinner controls to tell VERDI to use the layers you have specified. By default, a plot will initially display data for the minimum layer chosen in the **Layers** panel. The range of the layers available in the **Layer** spinner control at the top of the plot matches the subset of layers specified when the **Use Layer Range** box is checked. Subsetting a dataset's or formula's layer range affects plots produced with those data. Section 9.4 describes the precedence rules.




Figure 20: Areas Pane




Figure 21: Open Area File Browser




Figure 22: Open Area File: Select Name Field




Figure 23: Area Name Fields in Current Shapefile




Figure 24: Specify Time Step Range




Figure 25: Edit Layer Range in Formula Pane

## 9.3 Specify Domain Range

Datasets contain data for cells over a particular geographic area. VERDI refers to this area as a *domain*. By default, the entire domain contained in a dataset is used in creating plots. Use the **Controls** menu and then the **Set Row and Column Ranges** selection to define a subset of this domain for plotting.

## 9.4 Rules of Precedence for Subsetting Data

Use the subsetting feature to combine variables from two or more datasets that originally contained different but overlapping time steps and layers. Select identical subsets of the data available in each dataset such that their time steps and layers match. Then you can select variables from those datasets to create a formula and plot the data. Because both the **Dataset** pane and the **Formula** pane have the **Time Steps** and **Layers** panels described above, precedence rules determine which pane's settings take priority. It is important to understand these rules.

NOTE: You must check the appropriate boxes to have your selected ranges take effect.

- Dataset precedence: A subset of data specified in the **Dataset** pane takes precedence over any subset specified in the **Formula** pane. However, VERDI does not change the ranges displayed in the **Formula** pane when you select a subset on the **Datasets** pane. For example, if a dataset has a full time-step range of 0-48 and you select a time-step range of 2-40 on the **Dataset** pane, then the 0-48 time-step range that is listed for the formula in the **Formula** pane is not applicable. When you subsequently create a plot, the time-step range subset you chose in the **Dataset** pane (2-40) is displayed.
- Formula ranges: If you do not specify a subset for a particular data type (i.e., time steps or layers) in the **Dataset** pane, then any subsetting for that data type in the **Formula** pane takes effect.

# 10 Creating Plots

After creating a formula, you are ready to create and view some plots. The available plot types are shown on the buttons at the top of the VERDI main window: tile plot, areal interpolation plot, vertical cross section plot, time series plot, time series bar plot, scatter plot, and contour plot. All of these are described in this chapter. Note that not all datasets are appropriate for all plot types.

To generate a plot first highlight a formula in the list of formulas you have created in the **Formula** pane. You can also see the selected formula in the top right corner of the main VERDI screen (i.e., to the right of the plot buttons). Next, generate a plot by clicking on that plot type's button. If VERDI needs additional information to generate your chosen plot, a dialog box appears to prompt you for that information.

Each plot contains its own menu bar at the top of its window with options for configuring and exploring that type of plot. The menus may include **File**, **Configure**, **Controls**, **Plot**, and **GIS Layers**. The options for each of these menus are described in more detail in Chapter 11 Plot Menu Bar.




Figure 26: Tile Plot Example

## 10.1 Tile Plot

The **Tile Plot** displays gridded data defined as time steps and layers. It can also display grid cell time aggregate statistics. PDF: (Fig- 26)) or GitHub:[Figure 26](#) provides an example of the **Tile Plot** window.

Figure 26. Tile Plot Example

### 10.1.1 Time Selection and Animation Controls

At the top left of the Tile plot, the **Time Step** spin control can be used to change the time step by clicking the up or down arrow. Alternatively, highlight the value shown for the current time step, type in the desired value, and press the **Enter** key.

Buttons in the top right corner of the plot allow you to use play/stop, reverse, forward, and speed options to control the animation of the plot. Control the speed of the animation through the text box

labeled **Slow**; the default delay is 50 milliseconds between frames. If that text box is not visible, expand the plot window's width by clicking with the left mouse button on the right edge of the window and dragging to the right. Enter a number in the box for the length of the delay and then press the **Enter** key. A larger plot with multiple map layers may require a shorter delay between frames than a small zoomed-in plot with few map layers.

### 10.1.2 Layer Selection

The Layer displayed for the plot can be controlled by clicking on the up or down arrow for the **Layer** spin control in the top center of the plot.

### 10.1.3 Grid Cell Time Aggregate Statistics

The pull down menu option labeled **Stats** provides the option to display grid cell time-aggregate statistics (e.g., per-cell minimum, maximum, mean, geometric mean, median, first quartile, third quartile, variance, standard deviation, coefficient of variance, range, interquartile range, sum, time step of minimum, time step of maximum, maximum 8-hour average, and hours of noncompliance). Although you are still able to use the spinners to change the time step, the values and the chart's colors do not change.

VERDI calculates the grid cell time aggregate statistics as follows: For each cell  $(i,j,k)$  in the currently selected domain (independent of neighboring cells), the aggregated statistical value is calculated over the currently selected time steps. In other words, the aggregated statistical value is calculated for the plotted formula for cells  $(i,j,k,t_{\min}\dots t_{\max})$ , with the number of time steps  $n$ , where  $n=(t_{\max}-t_{\min}+1)$ .

- MINIMUM:  $\min(\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max}))$
- MAXIMUM:  $\max(\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max}))$
- MEAN:  $\text{SUM} / n$
- GEOMETRIC\_MEAN:  $((\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})))^{(1/n)}$
- MEDIAN: value at 50th percentile of (sorted { $\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})$ })
- FIRST\_QUARTILE: value at 25th percentile of (sorted ( $\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})$ )))
- THIRD\_QUARTILE: value at 75th percentile of (sorted ( $\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max})$ )))
- VARIANCE:  $((\text{var}(i,j,k,t_{\min})-\text{MEAN})^2 + (\text{var}(i,j,k,t_{\min}+1)-\text{MEAN})^2 + \dots + (\text{var}(i,j,k,t_{\max})-\text{MEAN})^2) / (n - 1)$
- STANDARD\_DEVIATION:  $\text{VARIANCE}^{0.5}$
- COEFFICIENT\_OF\_VARIANCE:  $\text{STANDARD\_DEVIATION} / |\text{MEAN}|$

- RANGE: MAXIMUM - MINIMUM
- INTERQUARTILE\_RANGE: THIRD\_QUARTILE - FIRST\_QUARTILE
- SUM:  $\text{var}(i,j,k,t_{\min}) + \text{var}(i,j,k,t_{\min}+1) + \dots + \text{var}(i,j,k,t_{\max})$
- TIMESTEP\_OF\_MINIMUM: 0-based time step when cell contains its minimum value
- TIMESTEP\_OF\_MAXIMUM: 0-based time step when cell contains its maximum value
- HOURS\_OF\_NON\_COMPLIANCE: number of time steps that the cell value exceeds a given threshold  $|\{\text{Var}(I,j,k,t(i)) > \text{threshold}\}|$
- MAXIMUM\_8HOUR\_MEAN:  $M_a$  ( $M_1, M_2, \dots, M_{n-8}$ ) where  $M_i = \text{mean}(\text{var}(i,j,k,t(i)), \text{var}(i,j,k,t(i)+1), \text{var}(i,j,k,t(i+2)), \dots, \text{var}(i,j,k,t(i+8)))$ , for  $i = 1..n-8$
- count: number of timesteps available in the dataset
- fourth\_max: fourth highest value for each grid cell (used to obtain the 4th highest value of your rolling 8 hr maximum CMAQ output file)
- custom\_percentile: default is  $> .12$  (use the text box) value at custom th percentile of( sorted  $(\text{var}(i,j,k,t_{\min}), \text{var}(i,j,k,t_{\min}+1), \dots, \text{var}(i,j,k,t_{\max}))$ )
- layer\_sum: Sum values at all layers (by default) or at layers within the user selected layer range set by “Use Layer Range” for each grid cell at each time step
- layer\_mean: layer\_sum/number of layers

#### 10.1.4 Specify Layer Range when use ‘layer\_sum’ and ‘layer\_mean’ from the above aggregated Statistics dropdown menu in a tile plot

User should check the checkbox of ‘use layer range’ and specify the layer range before clicking on the ‘Tile Plot’ button on the top menu for the specified layer range to take effect.

## 10.2 Areal Interpolation Plot

The **areal interpolation** plot displays the interpolated value of the selected formula for each polygon in the selected area file. Compare the colors of the polygons to those shown in the legend, to see the relative values of the formula for each polygon area. The Areal Interpolation Plot includes several capabilities that are not available for other plot types, so these are described below.




Figure 27: Areal Interpolation Plot: Area Average

### 10.2.1 Options Menu

The Areal Interpolation Plot menu contains an **Options** menu to allow the user to change the map to display either the Area Averages PDF:(Fig- 27)) or GitHub:(Figure 27), the Area Totals PDF:(Fig- 28)) GitHub:(Figure 28), or the value of the formula contained in the Gridded Dataset (uninterpolated) PDF:(Fig- 29)) GitHub:(Figure 29). The **Options** pull-down menu may also be used to display All area segments that are loaded in the area list, or to display only the area segments that are selected by highlighting the name field from the area list PDF:(Fig- 30)) or GitHub:(Figure 30).

### 10.2.2 Areal Values for Polygon Segment

To view the area, total value, and average value for a selected polygon segment use the mouse cursor to hover over a polygon on the map. The values are shown at the bottom left of the information panel PDF:(Fig- 31)) or GitHub:(Figure 31).




Figure 28: Areal Interpolation Plot: Area Totals




Figure 29: Areal Interpolation Plot: Show Gridded Data




Figure 30: Areal Interpolation Plot: Show Selected Areas




Figure 31: Areal Values for a Selected Polygon

### 10.2.3 View and Export Areal Interpolation Plot Data in Text Format

To view the average and total interpolation values for selected formulas in a spreadsheet format, right click on the Areal Interpolation Plot and select **Area Information PDF**: (Fig- 32) or GitHub: (Figure 32), then click on the radio button next to All, to select all area regions, click on the Formula Name, then click on OK. The Area Information Spreadsheet contains four columns: the identification number from the name field for the polygon, the total area, average interpolated value, and total interpolated value PDF: (Fig- 33) or GitHub: (Figure 33). At the top of the **Area Information** tab, the user may select **File>Export** to export the data to a spreadsheet file (Figure 34). The save popup window allows the user to specify with either a text (.txt) or comma-separated-values (\*.csv) format, also known as a comma-delimited text file (Figure 35).

### 10.2.4 Export Areal Interpolation Plot Data to Shapefiles

At the top of the **Area Information** tab PDF: (Fig- 36) or GitHub: (Figure 36), the user may select **File>Export Shapefiles** to export the data to a shapefile. In the Save popup window PDF: (Fig- 37) or GitHub: (Figure 37), input the name in the File Name field, and select file type: Shapefile (\*.shp). The data provided in the Area Information report (i.e., name, total area, average value, total value) are exported to the shapefile. A GIS program such as User-friendly Desktop Internet GIS (uDig; <http://udig.refractions.net/>), an open-source Java program, or QGIS (<http://qgis.org/en/site/>) may be used to view the shapefiles generated by VERDI. The shapefiles are saved as five separate files that must be kept together as part of the ESRI format (\*.shp, .dbf, .prj, .shx, and .fix). There are no units assigned to the data that are saved in the shapefile, so it is important for the user to keep a copy of the comma-delimited text file, or to keep some alternative text file that specifies the units for each data field.

## 10.3 Vertical Cross Section Plot

The **vertical cross section plot** allows you to show a slice of data PDF: (Fig- 38) or GitHub: (Figure 38). A popup dialog box PDF: (Fig- 39) or GitHub: (Figure 39) prompts you for information needed to create the plot. Enter either the column to be used (for an x-axis cross section) or the row to be used (for a y-axis cross section) in the plot. The current time step on the plot can be changed using the **Time Step** spinner control above the plot, which also changes the date and time shown in the bottom of the plot. There is also a **Column** spinner control to change the column number (or row number). The cross-section column number (or row number) is included in the title of the plot and changes as you change the spinner control.

## 10.4 Time Series Plot

The **time series plot** shows a line graph with the average values over time (Figure 40). The plot is made for the formula's selected domain, layer range, and time-step range. Each time step's data are averaged linearly to produce that time step's data point. The current layer can be changed using the **Layer** spinner control above the plot. The layer value listed in the title is updated when you change the layer.




Figure 32: Right Click on Area Plot

Area Information: DRYOX\_N[1] (1, 1)

File

**Area Information: DRYOX\_N[1] (1, 1)**

Name	Area (km2)	DRYOX_N[1] (kg)	DRYOX_N[1]_A (kg/hectare)
1315	5658.38434050896	24295.299	4.293681
1327	4517.340297232507	20979.955	4.6443157
1309	1904.1156421275293	8881.052	4.664135
1323	4394.539581212584	20308.246	4.6212454
1339	4106.715652683912	17286.227	4.209258
1363	1546.2970358313198	7484.6016	4.8403387
1384	5280.143705007377	26897.678	5.0941186
1372	1534.9417887454965	6786.978	4.421652
2220	9744.923296339746	32835.496	3.3694978
1389	3207.6620998844414	16537.137	5.155511
2222	2185.3123721549996	8540.771	3.9082613
1413	6299.966453170846	26559.135	4.2157583
2225	3373.9280370367483	12193.176	3.6139407
1404	2276.6516332328333	9307.507	4.088244
1417	3355.692452064106	15284.323	4.554745
1424	6173.504265627928	26991.078	4.3720837
1440	4379.134220601725	20332.229	4.642979
1473	2334.7802505662535	11956.992	5.1212497
1486	6085.506620610624	27568.72	4.5302258
1469	3087.0962621653107	14152.65	4.584454
1468	3734.9135064814936	14930.879	3.9976504
1443	2532.7375578157676	8613.673	3.4009337
1461	2618.965925796131	9094.851	3.4726877
1448	2928.2832605735425	9465.642	3.2324884
2232	5292.355608000654	13661.271	2.5813217
1526	1698.8355649584494	7819.1265	4.6026387
1491	4208.0303564634505	15216.295	3.6160138
1505	2217.3759696883976	8044.047	3.6277325
1545	6359.784945829492	29068.387	4.5706553
1537	3646.5112012747236	16419.758	4.5028677
1485	2711.955229380954	8375.645	3.0884154
1508	4035.2177271460914	11958.902	2.9636323
1569	3506.6646873289114	16469.916	4.696747
1553	4546.181824042358	14209.543	3.1255994
1502	2916.183998927327	9382.019	3.2172244
1531	4494.55431244175	14186.302	3.1563313
1601	6472.768208735124	25231.164	3.8980486
1616	2639.488172937004	9257.198	3.5071943
1607	2113.024859363581	9490.889	4.4916124

ArealInterpolation Area Information: DRYOX\_N[1] (1, 1)

Figure 33: Area Information in Columns

Area Information: DRYOX_N[2] (0, 0)			
Area Information: DRYOX_N[2] (0, 0)			
Name	Area (km <sup>2</sup> )	DRYOX_N[2] (kg)	DRYOX_N[2]_A (kg/ha)
1315	5655.875740826468	2433536.5	4.302669
1327	4515.625631195322	2046187.5	4.5313487
1309	1903.3636596603767	966721.5	5.0790167
1323	4392.830729537164	2160675.8	4.918641
1339	4105.370007776452	1804585.9	4.395672
1363	1545.727366164398	704919.7	4.56044
1384	5278.531687088094	2507917.2	4.7511644
1372	1534.467680366486	667539.25	4.3502984
2220	9742.857916457127	3446319.2	3.5372775
1389	3206.723523436829	1596897.2	4.9798403
2222	2184.7607501077305	902749.25	4.132028
1413	6298.539515028009	2538349.5	4.030061
2225	3373.2908771270318	1293966.2	3.835917
1404	2276.128379094424	963203.0	4.2317605
1417	3355.0225950614754	1514861.4	4.5152044
1424	6172.757287822339	2985992.2	4.837372
1440	4378.35502573675	2168069.5	4.9517903
1473	2334.434805271438	1042260.25	4.464722

Figure 34: Export to a Text File




Figure 35: Name and Save the Text File

Area Information: DRYOX_N[2] (0, 0)			
File	Area Information: DRYOX_N[2] (0, 0)		
Export	Export Shape Files	Area (km2)	DRYOX_N[2] (kg)
1315		5655.875740826468	2433536.5
1327		4515.625631195322	2046187.5
1309		1903.3636596603767	966721.5
1323		4392.830729537164	2160675.8
1339		4105.370007776452	1804585.9
1363		1545.727366164398	704919.7
1384		5278.531687088094	2507917.2
1372		1534.467680366486	667539.25
2220		9742.857916457127	3446319.2
1389		3206.723523436829	1596897.2
2222		2184.7607501077305	902749.25
1413		6298.539515028009	2538349.5
2225		3373.2908771270318	1293966.2
1404		2276.128379094424	963203.0
1417		3355.0225950614754	1514861.4
1424		6172.757287822339	2985992.2
1440		4378.35502573675	2168069.5
1473		2334.434805271438	1042260.25

Figure 36: Export Shapefile




Figure 37: Name and Save Shapefile




Figure 38: Vertical Cross Section Plot




Figure 39: Vertical Cross Section Dialog Box




Figure 40: Figure40




Figure 41: Time Series Bar Plot

## 10.5 Time Series Bar Plot

The **time series bar plot** shows average values over time in a bar plot format (Figure 41) rather than a line format (Figure 40). Other than that, the description of this plot type is the same as for the time series line plot (see Section 10.4).

## 10.6 Scatter Plot

The **scatter plot** shows the relationship between two formulas using dots PDF:(Fig- 42)) or GitHub:(Figure 42). Specify the formulas using the dialog box that comes up before the plot is displayed (Figure 43). The current time step and layer can be adjusted using the spinner controls above the plot. The data from a scatter plot may be exported by selecting the **File** menu option and then selecting Export data. If your dataset has more than one layer or time step, a popup window (see PDF:GitHub:Figure 44) allows you to specify whether you want to export the data for the current layer, or for all layers, and for the current time step, or for all time steps. Specify the time and layer ranges, and then click the **OK** button. A Save popup dialog box appears. Navigate to the directory in which you want to save this file and enter a file name with a .csv extension. The CSV file will be comma-delimited, and will contain the following columns of data: layer, time step, x-axis formula,




Figure 42: Scatter Plot

*y*-axis formula. You can open this file in a spreadsheet program if your data does not contain too many rows (e.g., 65,536 or 1,048,576 depending upon version of Microsoft Excel).

## 10.7 Contour Plot

The **contour plot** shows a three-dimensional (3-D) representation of values for a gridded dataset (e.g., one that can be used in the Tile Plot) PDF:(Fig- 45)) or GitHub:(Figure 45). Note that the 3-D contour plot is displayed in its own window (i.e., not in the VERDI window). The current time step and layer can be adjusted using controls above the plot. You can also animate the plot over time using an option in the **Plot** pull-down menu PDF:(Fig- 46)) or GitHub:(Figure 46). In addition, the contour plots can be rotated in three dimensions to achieve different viewing angles by using the left mouse button to grab and rotate the plot PDF:(Fig- 45)) or GitHub:(Figure 45).




Figure 43: Scatter Plot Dialog Box

## 11 Plot Menu Bar

Each VERDI plot contains a menu bar with options specific to that type of plot. The menu options at the top of the Tile Plot and Areal Interpolation Plot include those shown in [Table 11-1](#).

Table 11-1. Tile and Areal Interpolation Plot Pull-down Menu Options

File	Configure	Controls	Plot	GIS Layers
Print	Configure Plot	Zoom (not for MPAS netCDF)	Time Series of Probed Cell(s)	Add Map Layers
Export as Image/GIS	Load Configuration	Probe (not for MPAS netCDF)	Time Series Bar of Probed Cell(s)	Configure GIS Layers
	Save Configuration	Set Row and Column Ranges	Time Series of Min. Cell(s)	Set Current Maps as Plot Default
		Show Grid Lines (MPAS:Show Cell Borders)	Time Series of Max. Cell(s)	
		Show Lat/Lon (MPAS:Show Wind Vectors)	Animate Plot	
			Add Overlay (not for MPAS netCDF)	

File	Configure	Controls	Plot	GIS Layers
		For MPAS: Show Wind Vectors		

The menu options at the top of the Vertical Cross Section, Time Series, Time Series Bar Plot and Scatter Plot include those shown in [Table 11-2](#). Most options are common to all plots, and function in the same way (unless the option is grayed out). Therefore, this chapter is organized by menu instead of by plot type.

Table 11-2. Vertical Cross Section, Time Series, Time Series Bar, Scatter Plot Pull-down Menu Options

File	Configure	Controls
Print	Configure Plot	Zoom
Export as Image	Load Configuration	Probe
	Save Configuration	Show Lat/Lon
	Load Chart Theme	
	Edit Chart Theme	
	Save Chart Theme	

## 11.1 File Menu

Options in the **File** menu include printing a plot and exporting a plot to an image file. Plots can be saved as BMP, EPS, JPEG, PNG, TIFF image files or as the Shapefile format. The ASC format is a text file containing the cell values.

## 11.2 Configure Menu

The **Configure** pull-down menu contains the following options: Configure Plot, Load Configuration, and Save Configuration. When you want to see your changes on the plot, press the **Apply** button. When you have finalized the settings for your plot, click the **OK** button to close the Configure Plot dialog box.

### 11.2.1 Configure Plot

PDF:(Fig- 48) or GitHub:[Figure 48](#) through PDF:(Fig- 51) or GitHub:[Figure 51](#) show the dialog boxes that appear when you select Configure Plot. The **Configure Plot** dialog box contains four tabs: **Titles**, **Color Map**, **Labels**, and **Other**.

- **Titles tab:** PDF:(Fig- 48) or GitHub: [Figure 48](#) shows the selections on this tab that you can use to edit title text and select the font type, size, and color for the title and two subtitles of the plot.




Figure 44: Scatter Plot Export Data into a CSV file




Figure 45: Contour Plot

File	Configure	Controls	Plot
Print	Configure Plot	Show Lat/Lon	Animate Plot
Export As Image	Load Configuration	Show IsoContours	
	Save Configuration		

Figure 46: Contour Plot Menu Options




Figure 47: Rotated Contour Plot

Subtitles may be turned on or off by selecting or deselecting the check box for each subtitle. If a check box is not selected the associated text, font type and size, and color boxes are grayed out. However, you must provide a title or VERDI will provide its default title for you. To blank out the title you must select it and then enter spaces for the name of the title. If you deselect the title VERDI will provide its default title for you.

- **Text:** Enter the desired text directly in the textbox. You can enter text for the plot's title and up to two optional subtitles.
- **Use Unicode in Text:** Unicode characters can be used with text, for example, if you want to display “2.5” as subscripts in PM2.5, you can insert Unicode “2082” for subscripted 2, Unicode “2024” for a dot and Unicode “2085” for subscripted 5 in the **Text** field.
- **Font:** Press the **Select** button to the right of the Font line for the title or subtitle you wish to change. Your system's standard Select Font dialog box is then displayed for you. Select a font family, font style, and size; press the **OK** button to return to the Configure Plot tab.
- **Color:** Press the **Select** button to the right of the Color line for the title or subtitle to edit. There are five types of color palettes that you can use to select a color – Swatches, HSV, HSL, RGB, and CMYK – each on its own tab. When you select a color examples of its use are shown in the Preview portion of the Select Color window. Select the **OK** button to accept the color and return to the Titles tab of the Configure Plot dialog box.
- **Color Map tab:** This tab is available for only the Tile and Areal Interpolation Plots (see PDF:(Fig- 51) or GitHub:[Figure 51](#)). This tab provides many widgets for you to configure your legend colors, break points, range, etc. You can select the number of tiles, the palette type to be used, the color interval, the number format, and the scale.
- **Number of Tiles:** Start by selecting the number of tiles at the top of the pane. Options in some other selections, such as the available palettes and break points, change as you vary the number of tiles.
- **Palette Type:** Three palette types are available: Diverging, Qualitative, and Sequential. Diverging has dark colors at the maximum and minimum of the range and light colors in the middle. Qualitative has a mixture of colors. Sequential has a dark color on one end (typically the maximum) with lighter shades of the same color proceeding to the lightest shade at the minimum. The color palettes frequently associated with air quality modeling results are the Tile Plot default and the Newton RGB palettes of the Sequential type.
- **Reverse:** The reverse button reverses the order of the colors in the selected palette. For example, if a sequential palette is used, the reverse button changes the color intensities such that the darkest color is at the minimum instead of the maximum of the scale.




Figure 48: Configure Plot, Titles Tab





Figure 49: Configure Plot, Titles Tab

Figure 50: PM<sub>2.5</sub> Tile Plot with Title Applied




Figure 51: Configure Plot, Color Map Tab

- **Interval:** The interval can be set to either Automatic or Custom. The typical setting is Automatic, meaning that VERDI calculates the interval break points based on the minimum and maximum values in the dataset. Change the interval to Custom if you need to edit the values for Interval Start for each color tile.
- **Number Format:** To specify the number format used in the map legend, enter the format `leading non-digit[width].[decimals][E][0]` Then click the Rebuild button. NOTE: If you use any character other than E or e, VERDI will display each value as a decimal followed by that character.

**Explanation of the format:**

[width]: sum of [decimals] + 1 for . + desired number of places before the .; is recomputed in code if too small

.. separator between the values for [width] and for [decimals]

[E]: optional; if present use scientific notation (e.g., 2.33E-2) otherwise display in regular decimal notation (e.g., 0.0233)

- **Scale:** Select either Linear or Logarithmic. The interval start values are automatically adjusted when you change the scale.
- **Min and Max:** The minimum and the maximum values are computed for the data to be plotted. If you set the Interval to Automatic, you can change the values for the minimum and maximum. Then, press the Rebuild button and the Apply button to see your changes both in the legend and on the map. You cannot edit the minimum or the maximum value if the Interval is set to Custom. Instead, directly edit the Interval Start values; the Interval Start value for the lowest interval is the minimum value.
- **Rebuild:** The Rebuild button is either active or inactive (i.e., grayed out) depending upon what other widgets are active. If you make changes and the Rebuild button is active, press it before continuing.
- **Labels tab:** PDF:(Fig- 52) or GitHub:[Figure 52](#) shows widgets for you to edit more labels on your plot. There are four tabs through which you can edit the labels of the Domain Axis (x-axis), the Range Axis (y-axis), Legend, and Footer.
- **Domain Axis:** This tab has two parts: Label and Ticks. Use the Label panel the same way as the Titles tab (above) by editing the Text, Font, and Color. The Ticks panel allows you to change the labels associated with the ticks on the Domain Axis. The “Show Tick Labels” checkbox is typically checked, but you can uncheck it to not show any ticks or labels on this axis. Number allows you to decrease the number of tick labels. Note that you cannot increase the number of ticks via this screen and the values of the ticks do not change; you are effectively turning tick labels on/off via this checkbox. The Font and Color widgets work the same as for the Titles tab.
- **Range Axis:** All the widgets on this tab are the same as on the Domain Axis tab. You are just making the changes for the Range Axis. PDF:(Fig- 53) or GitHub:[Figure 53](#) shows an example plot where the number of Tick Labels has been reduced in both the Range Axis and the Legend, but the number of tick labels has not been reduced in the Domain Axis.




Figure 52: Configure Plot, Labels Tab




Figure 53: Example Plot with Selected Tick Marks for Range Axis and Legend

- **Legend:** The Show Legend checkbox defaults to checked, which indicates that the legend should be shown. If you do not want a legend, uncheck that checkbox. All the widgets on this tab are the same as on the tabs for the axes. Use the Label part to designate and format the label that appears vertically in the left side of the legend box. The tick labels are for the boundaries between colors in the legend. If you uncheck the Show Tick Labels checkbox, the tick labels disappear from the legend.
- **Footer:** This tab is divided into three parts: Line One, Line Two, and Observational Data Legend. Lines One and Two are for the first and second lines of footers, respectively. VERDI automatically creates these lines for you, but you can either edit or remove them here. You cannot enter text for the Observational Data Legend if you do not have observational data on your plot.
- **Other tab:** As shown in PDF:(Fig- 54) or GitHub:[Figure 54](#)), use the widgets on this tab to enable or disable showing the grid lines, to select the color of grid lines, and to select the series color.

### 11.2.2 Save Configuration

If you have made changes to the configuration of a plot, and want to reuse that configuration for other plots, use the **Save Configuration** selection from the **Configure** menu. It is very important (1) to name the file in a manner that you will remember what it contains and (2) to save the file in a logical place so you will be able to find it when you need it.

The file name should indicate the formula name, the dataset, and the type of plot from which it was saved. Also, use the “.cfg” extension to indicate that it is a configuration file. An example file name is <FormulaName><DatasetFilename><PlotType>.cfg, or “O3\_CCTM\_base\_tile.cfg”.

You may decide to keep your configuration files with projects to which they relate or in a common directory. When you save your configuration file, VERDI uses the value of verdi.config.home in your config.properties file as the default location. If you want to save the configuration somewhere else, browse to the location. Enter the file name and press the **Save** button.

When you choose to save your configuration, VERDI displays a popup box asking if you want to save the title/subtitles. Although the configuration files generated by VERDI look similar to HTML or XML files, they are just text files containing tags compatible with the parser in VERDI. You can look at the contents of these files in a plain text editor (e.g., Notepad), but be very careful if you decide to change their contents; you could make the file unusable.

#### 11.2.2.1 Configuration file xml format

This example configuration file contains 11 colors, with a color scheme that diverges, from a minimum value of -2.5 to a maximum value of 2.5. An enhancement was made to use the hexadecimal format to save the color values, beginning in VERDI\_2.1.5. VERDI can read a configuration file that uses either hexadecimial values or 32 bit integer values saved prior to this enhancement. This allows the user to use color wheels available online to customize their plots.




Figure 54: Other Tab

```

<PlotConfig>
    <property type="java.awt.Color" key="anl.verdi.plot.con...
        <property type="java.lang.Integer" key="...
            <property type="java.awt.Color" key="...
                <property type="java.awt.Font" key="...
                    <property type="java.awt.Color" key="...
                        <property type="java.awt.Font" key="...
                            <ColorMap intervalType="CUSTOM" scaleTy...
                                <Format type="java.text.DecimalFormat" pattern="#0.00" />
                                <Scale description="Color Scale">
                                    <Step>-2.5</Step>
                                    <Step>-2.0</Step>
                                    <Step>-1.5</Step>
                                    <Step>-0.5</Step>
                                    <Step>-0.01</Step>
                                    <Step>0.01</Step>
                                    <Step>0.05</Step>
                                    <Step>0.5</Step>
                                    <Step>1.0</Step>
                                    <Step>1.5</Step>
                                    <Step>2.0</Step>
                                    <Step>2.5</Step>
                                </Scale>
                                <Palette description="dark red to light to dark blue" reverseColors="false">
                                    <Color>#67001F</Color>
                                    <Color>#B2182B</Color>
                                    <Color>#D6604D</Color>
                                    <Color>#F4A582</Color>
                                    <Color>#FDDBC7</Color>
                                    <Color>#F7F7F7</Color>
                                    <Color>#D1E5F0</Color>
                                    <Color>#92C5DE</Color>
                                    <Color>#4393C3</Color>
                                    <Color>#2166AC</Color>
                                    <Color>#053061</Color>
                                </Palette>
                            </ColorMap>
                            <property type="java.awt.Font" key="...
                                <property type="java.lang.Boolean" key="...
                                    <property type="java.lang.String" key="...
                                        <property type="java.awt.Font" key="...
                                            <property type="java.awt.Color" key="...
                                                <property type="java.lang.String" key="...
                                                    <property type="java.lang.String" key="...
                                                        <property type="java.lang.String" key="...
...

```

```

<property type="java.awt.Color" key="anl.verdi.formula.FormulaPlotConfig.BackgroundColor">
<property type="anl.verdi.formula.FormulaPlotConfig">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.ShowXAxis">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.ShowYAxis">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.XLabel">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.YLabel">
<property type="java.awt.Color" key="anl.verdi.formula.FormulaPlotConfig.XAxisColor">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.XAxisLabelColor">
<property type="java.awt.Color" key="anl.verdi.formula.FormulaPlotConfig.YAxisColor">
<property type="java.awt.Font" key="anl.verdi.formula.FormulaPlotConfig.XAxisFont">
<property type="java.awt.Font" key="anl.verdi.formula.FormulaPlotConfig.YAxisFont">
<property type="java.lang.Integer" key="anl.verdi.formula.FormulaPlotConfig.XAxisFontSize">
<property type="java.awt.Color" key="anl.verdi.formula.FormulaPlotConfig.XAxisTextColor">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.XAxisVisible">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.YAxisVisible">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleColor">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.YAxisTitleColor">
<property type="java.awt.Font" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleFont">
<property type="java.awt.Font" key="anl.verdi.formula.FormulaPlotConfig.YAxisTitleFont">
<property type="java.lang.Integer" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleFontSize">
<property type="java.awt.Color" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleTextColor">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleVisible">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.YAxisTitleVisible">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleLabelColor">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.YAxisTitleLabelColor">
<property type="java.awt.Font" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleLabelFont">
<property type="java.awt.Font" key="anl.verdi.formula.FormulaPlotConfig.YAxisTitleLabelFont">
<property type="java.lang.Integer" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleLabelFontSize">
<property type="java.awt.Color" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleLabelTextColor">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleLabelVisible">
<property type="java.lang.Boolean" key="anl.verdi.formula.FormulaPlotConfig.YAxisTitleLabelVisible">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.XAxisTitleLabelLabelColor">
<property type="java.lang.String" key="anl.verdi.formula.FormulaPlotConfig.YAxisTitleLabelLabelColor">
</PlotConfig>
```

### 11.2.3 Load Configuration

To load a plot configuration file, first create a new plot that is of the same type and uses the same formula as that within the configuration file. Then select the **Load Configuration** option from the **Configure** menu on that plot. An **Open File Dialog** window enables you to navigate to the directory in which you saved the configuration file. Select the file you need and press the **Open** button. The plot title (if saved), color map, and other plot configuration features are then applied to the plot.

Note that it is possible to load a saved configuration file that does not apply to the selected plot. VERDI may try to load what it can, which may result in something other than what you expected. Therefore, before loading a saved plot configuration check carefully to be sure the plot type and formula of the configuration file match those of the new plot.

You can also load configuration files in batch or command line scripts by setting the parameter config-File (e.g., configFile=C:\User\username\VERDI\_2.2\data\configs\o3\_10bin.cfg).

#### 11.2.4 Load Chart Theme

A Chart Theme sets the background colors and fonts for a Vertical Cross Section, Time Series, Time Series Bar, and Scatter plot. A loaded theme applies to each of these types of plots when you create them. This allows the user to customize and make the plots uniform for publishing purposes.

To load a chart theme, select the **Configure** menu on the plot and then the **Load Chart Theme** menu item. An **Open** Dialog window enables you to navigate to the verdi.config.home directory set in your config.properties file under the verdi directory in your home directory. As an example, select the **white.theme** theme file and press the **Open** button. The plot title, color map, and other plot configuration features are then applied to your current plot.

#### 11.2.5 Edit Chart Theme

To edit a chart theme, select the **Configure** menu on the plot and then the **Edit Chart Theme** menu item. An **Edit Chart Theme** dialog frame opens. The top part of the Dialog is shown in PDF:(Fig- 55) or GitHub:[Figure 55](#); use the slider to view the bottom portion of the Dialog as shown in PDF:(Fig- 56) or GitHub:[Figure 56](#). Click **Select** next to the Text item you would like to change and a Select Font Dialog opens PDF:(Fig- 55) or GitHub:[\(Figure 55\)](#). To change the color of an item, click **Select** next to it, and a Select Color Dialog frame opens PDF:(Fig- 56) or GitHub:[\(Figure 56\)](#). Click **Apply** at any time to see your changes. When you are finished click **OK** to close the Edit Chart Theme window.

#### 11.2.6 Save Chart Theme

To edit a chart theme, select **Save Chart Theme** option from the Configure menu on the plot. A **Save** Dialog will open PDF:(Fig- 57) or GitHub:[\(Figure 57\)](#)

### 11.3 Controls Menu

The **Controls** pull-down menu contains the following options: Zoom (not available for MPAS netCDF), Probe(not available for MPAS netCDF), Set Row and Column Ranges, Show Grid Lines (or Show Cell Borders for MPAS netCDF), and Show Lat/Lon (or Show Wind Vectors for MPAS netCDF).

#### 11.3.1 Zoom

To zoom in and enlarge a subdomain of the plot, select the **Zoom** option. Then use your left mouse button to draw a rectangle around your region of interest on the plot. To zoom out click on the chart using your right mouse button to bring up the context menu PDF:(Fig- 60) or GitHub:[\(Figure 60\)](#). Move your cursor over either Zoom Out or Max Zoom Out and press the left mouse button. The Zoom




Figure 55: Top Portion of Edit Chart Theme Window




Figure 56: Bottom Portion of Edit Chart Theme (Bg=background, Grdln=grid line)




Figure 57: Select Font in Edit Chart Theme Window




Figure 58: Select Color in Edit Chart Theme Window

Out selection performs a step zoom and the Max Zoom Out selection zooms out to the full extent of the plot.

The selections in the context menu are a little different for the time series plot. Zoom In and Zoom Out open another level of menus where you can select Both Axes, Domain Axis, or Range Axis. The Auto Range selection opens another submenu with the same 3 selections; use the Auto Range, Both Axes submenu to reset both axes to the full extent of both the domain and the range.

### 11.3.2 Probe

To determine the data value at a specific point or within a subregion, select the **Probe** option.

#### 11.3.2.1 Probe at a Single Point

To probe a single data point, use the mouse to hover the cursor over a single point on the plot (e.g., one value on a time series plot, one grid cell on a tile plot); the coordinates of the point are shown in the lower right-hand side of the plot in the format (column, row) or (longitude, latitude) if you have selected Show Lat/Lon. Once you click on the grid point of interest, the value of the datum at that grid point is displayed in the lower left-hand area of VERDI main window PDF:(Fig- 60) or GitHub:([Figure 60](#)) in the format (time step, layer, row, column):value.




Figure 59: Save Dialog




Figure 60: Right-Click on Tile Plot to Zoom Out




Figure 61: Click on Plot to Probe: Data Value Shown in Lower Left of VERDI, Latitude/Longitude Values Shown in Lower Right




Figure 62: Data Window Showing Probed Values for Region of Interest

### 11.3.2.2 Probing a Domain Region of Data

When you have Probe selected you can examine the values of a region of locations. Use your mouse to draw a rectangle on the plot by clicking on a location, dragging the mouse to the opposite corner of your desired rectangle, and then releasing the mouse button. VERDI will create a data window displaying the grid values and will place it in the plot area of the VERDI main window as a tabbed window PDF:(Fig- 61) or GitHub:(Figure 61). The File>Export menu option at the top of the spreadsheet allows you to save probed data as a comma-delimited text file (\*.csv).

### 11.3.3 Set Row and Column Ranges

The **Controls>Set Row and Column Ranges** menu item displays a popup window that allows you to configure the minimum and maximum values used in the columns (\**x-axis domain*) and rows (\**y-axis range*) PDF:(Fig- 64) or GitHub: (Figure 64). Specify the values and then click **OK** to redraw the plot.

### 11.3.4 Show Grid Lines

Use the Show Grid Lines selection on the Controls menu if you want to have grid lines overlaid on your plot. PDF:(Fig- 65) or GitHub: Figure 65 shows one reason for wanting grid lines. There is a set




Figure 63: Select Set Row and Column Ranges




Figure 64: Select Set Row and Column Ranges

of grid cells with relatively high ozone values for the selected time step and layer. By zooming in on the plot and then showing the grid lines, the individual cells can be identified for further analysis.

### 11.3.5 Show Latitude and Longitude

To view the latitude and longitude values for a point on the plot, select the Show Lat/Lon option on the **Controls** menu. Then, hover your cursor over a location to see its latitude and longitude. The lat/lon coordinates are displayed in the lower right-hand side of the window PDF:(Fig- 66) or GitHub: ([Figure 66](#)). The option to display the lat/lon coordinates may be selected, and works with either the Zoom or the Probe option.

### 11.3.6 Show Cell Borders (MPAS files)

VERDI can visualize the model grid structure to verify that the mesh generated is what was intended for MPAS files that only contain the mesh (no model data) or for MPAS files that contain both the mesh and the model data. To visualize the MPAS mesh, select the MPAS file, and then if it is a MPAS file with only the mesh, select the meshStructure variable and then create a Tile Plot. For regular MPAS files with model output, you can click on any variable and create a tile plot. From the Tile Plot menu, use the **Controls** menu, then select the Show Cell Borders, and then zoom in or zoom out to visualize the mesh or grid for the region of interest in the MPAS file PDF:(Fig- 67) or GitHub: ([Figure 67](#)).

## 11.4 Plot Menu Options

The **Plot** pull-down menu PDF:(Fig- 68) or GitHub: ([Figure 68](#)) contains the following options: Time Series of Probed Cell(s), Time Series Bar of Probed Cell(s), Time Series of Min. Cell(s), Time Series of Max. Cell(s), Animate Plot, and Add Overlay. NOTE: The Time Series of Probed Cells and the Time Series Bar of Probed Cells selections are grayed out until you select a grid cell or multiple grid cells using the Controls>Probe menu selection.

### 11.4.1 Time Series Plots

The Time Series of Probed Cell(s) and Time Series Bar of Probed Cell(s) allows the user to select a set of cells, and then produce a time series or time series bar plot of the chosen subset of probed cells. The Time Series of Min. [or Max.] Cell(s) option creates a time series plot using data for the currently selected formula at that formula's domain, layer range, and time step range. The minimum [or maximum] value of that formula over the domain and layer range at that time step is calculated by VERDI and used for each of the time step's data points. For examples of the Time Series Plot and the Time Series Bar Plot see PDF:(Fig- 41) or GitHub: [Figure 40](#) and [Figure 41](#), respectively.

### 11.4.2 Animate Plots

You can create an animated plot by selecting the Animate Plot option. The Time Series and Time Series Bar Plots do not have an Animate Plot option. The plots that may be animated include: Tile,




Figure 65: Show Grid Lines on a Tile Plot




Figure 66: Lat/Lon Values Shown in Lower Right of VERDI




Figure 67: MPAS Mesh Structure Visualized in VERDI Tile Plot




Figure 68: Plot Menu Options




Figure 69: Animate Plot Dialog Box

Areal Interpolation, Vertical Cross Section, and Contour Plot. An Animate Plot dialog box PDF:(Figure 69) or GitHub:(Figure 69) appears, allowing you to save animations either as an animated GIF with a file extension of .gif or as a QuickTime movie with a file extension of .mov. This **Plot** menu option is plot-specific and so does not allow you to animate more than one plot at a time. To animate multiple plots, you will need to use the **PLOTS** pull-down menu at the top of the VERDI main window; see Section 5.2.2, “Animate Tile Plots.”

### 11.4.3 Add Overlays

VERDI supports two types of overlays – observations and vectors. For both types of overlays you may need to add data from another data file onto the underlying plot.

#### 11.4.3.1 Observational Data Overlays

It is useful to visually compare the results contained in model output datasets with the data points in observational datasets. You can do this by creating a Tile Plot of the model output and then overlaying it with observational data points. The observational dataset needs to be in a csv- or tab-delimited format or a Models-3 I/O API observational data format. See Chapter 13 for more information about how to convert AIRS observational data into this latter format.

Sample observational data are provided in the directory \$VERDI\_HOME/data/obs so you can create a sample Observational Data Overlay Plot. Follow these instructions to create your plot.

- Load a model output dataset.

- Load an observational dataset. Note that an *OBS* label appears to the right of the dataset name in the **Dataset** pane.
- Double-click on a variable in an observational dataset and add it to the **Variable** pane. Note that an *OBS* label appears to the right of the dataset name in the **Variable** pane.
- Create a formula in the **Formula** pane using a variable from the ***model output*** dataset. Use this formula to create a tile plot. (NOTE: If you attempt to use a formula that contains a variable from an observational dataset, the following error will occur: “Error while evaluating formula: Selected dataset is observational.”)
- Select Add Overlay>Observations from the tile plot’s **Plot** menu to view observational data as an overlay on a tile plot.
- An **Observation** dialog box PDF:(Fig- 70) or GitHub: ([Figure 70](#)) appears containing the variables that are available in the observational dataset. Select the observational variable to overlay on the Tile Plot from the Observation Details list. Multiple observational dataset variables can be overlaid on a Tile Plot.
- You can control the appearance of the symbols representing the observational data. The stroke size controls the thickness of the line used to draw the symbols; the shape size controls their diameter. You can use up to six different open-area shapes—circle, diamond, square, star, sun, and triangle—to distinguish among multiple observational datasets. A circle is the default symbol shape.
- Select **Add Variable** and then **OK** to overlay the observational data on the tile plot PDF:(Fig- 71) or GitHub:([Figure 71](#)).

Repeat the above process to add multiple variables. To remove the symbols for a variable on an observational data overlay, or to reset their size, shape, or stroke thickness, reopen the **Observation** dialog by using Add Overlay>Observations, select the observational variable you want to adjust, and then change its stroke size, shape size, or symbol. You can also remove a variable or move it up or down in the list. When you are finished click the **OK** button.

The center of the observational data point corresponds to the lat/lon value that is provided in the Models-3 I/O API observational data file. If observations are collocated, they are placed on top of one another. If that happens you may want to select different symbols or sizes for each dataset and place them from largest on the bottom to smallest on the top.

#### 11.4.3.2 Vector Overlays

Follow these instructions to add a vector overlay to a Tile plot. Typically, these are created to show wind speed and direction on a plot of gridded air quality data. The length of the calculated vectors is proportional to their magnitude.

- Create your Tile Plot.




Figure 70: Tile Plot Observation Dialog




Figure 71: Tile Plot with Observational Data Overlay

- If the data for your vectors are not in the same dataset, load the correct one and select the formulas that you will need for the vectors.
- Select the Add Overlay>Vectors option from the tile plot's **Plot** pull-down menu PDF:(Fig- 72) or GitHub:([Figure 72](#)).
- Select the two components of your vector in the Vector Overlay dialog box PDF:(Fig- 72) or GitHub:([Figure 72](#)). Typically, these are the East-West (u) and North-South (v) components of the wind. Assign the u component to Horizontal and the v component to Vertical.
- Specify the Vector Sampling Increment value to specify how many vectors are displayed, for example for every vector (increment=1), every third vector (increment=3), every fifth vector (increment=5)
- Click the **OK button** and the vector overlays are displayed on the plot.

NOTE: At this time you cannot control how the vectors are displayed, and there is no option to remove the vectors from the plot. If you need to make a change, you must start again with your Tile Plot.

Currently, vectors are plotted in the center of the grid cell. UWIND and VWIND are typically obtained from METCRO3D, which are defined at dot points or cell corners. Plotting the wind vector at their calculated locations will be added to the Tile Plot in a future release.

An example of an ozone concentration Tile Plot with a wind vector overlay is shown in Figure PDF:Fig- 73 or GitHub:[Figure 73](#). The length of each vector is proportional to its length. The direction of the vector is calculated from the direction and magnitudes of its two components. This figure illustrates how the wind changes speed and direction in this portion of the modeling domain for layer 1, time step 1.

## 11.5 GIS Layers

The **GIS Layers** menu contains the following options: Add Map Layers, Configure GIS Layers, and Set Current Maps as Plot Default. All map layers provided with VERDI are shapefiles.

### 11.5.1 Add Map Layers

Use the **Add Maps Layers** option in the **GIS Layers** menu to add maps to a Tile Plot or Areal Interpolation Plot PDF:(Fig- 74) or GitHub:([Figure 74](#)). Note that all GIS layers must be shapefiles.

A selection of default maps—including World, North America. USA States, USA Counties, HUCs, Rivers, Roads and Satellite images retrieved from opentopomap.org —can be selected or deselected by clicking on the respective menu selection. A check mark then appears or disappears next to the chosen map name, and the selected map appears on the plot. Shapefile, Citation:

- cb\_2018\_us\_state\_500k, 2018 TIGER/Line Shapefiles(machine-readable data files) prepared by the U.S. Census Bureau, 2018




Figure 72: Vector Overlay Dialog Box




Figure 73: Wind Vector Overlay on an Ozone Tile Plot




Figure 74: Add Map Layers

- ne\_10m\_rivers\_lake\_centerlines, Made with Natural Earth. Free vector and raster map data @ [naturalearthdata.com](http://naturalearthdata.com).
- ne\_10m\_roads, Made with Natural Earth. Free vector and raster map data @ [naturalearthdata.com](http://naturalearthdata.com).
- ne\_50m\_admin\_0\_countries, Made with Natural Earth. Free vector and raster map data @ [naturalearthdata.com](http://naturalearthdata.com).
- ne\_50m\_admin\_1\_states\_provinces\_lakes, Made with Natural Earth. Free vector and raster map data @ [naturalearthdata.com](http://naturalearthdata.com).
- Department\_of\_State\_Valid\_QGIS, Made with U.S. Department of State Large Scale International Boundaries (LSIB) dataset, <https://hiu.state.gov/data/>
-




Figure 75: Add Satellite Image Layer

### 11.5.2 Add Satellite Image Layer

Use the **Add Maps Layers** option in the **GIS Layers** menu and check the box next to Satellite to add satellite images to a Tile Plot or Areal Interpolation Plot PDF:(Fig- 75) or GitHub:(Figure 75). Note that the Satellite Image Layers are provided by the tile provider: <https://opentopomap.org/about/>

### 11.5.3 Configure GIS Layers

To show an additional map on the plot, select the **Configure GIS Layers** option in the **GIS Layers** menu. When you click on this item, a dialog box titled Manage Layers gives you the following options: Move Up, Move Down, and Remove Layer PDF:(Fig- 76) or GitHub:(Figure 76). The Edit Layer option has been greyed out.

- To rearrange the order in which the GIS layers are displayed on the plot, select a layer in the Manage Layers dialog box, and then select Move Up or Move Down. Click the **OK** button to reposition the order of that layer within the list. If the layers that you are selecting are boundaries




Figure 76: Manage Layers Dialog Box

and were created to have a transparent fill, then rearranging the order of the layers will not change the look of the boundaries on the plot.

- To remove a GIS layer from the plot, select that layer in the list and select Remove Layer. Then click the **OK** button to remove it.

## 12 Supported Grid and Coordinate Systems (Map Projections)

VERDI makes calls to the netCDF Java library to obtain the grid and coordinate system information about the data directly from the model data input files when the input data files are self-describing netCDF files (MCIP, SMOKE, CMAQ, WRF, MPAS, MPAS-CMAQ). The available tile plot options vary depending on the meta data convention in the files: I/O API (M3IO) data convention (MCIP, SMOKE, CMAQ), CAMx Gridded Data Convention, WRF netCDF Data Convention, and MPAS netCDF Data Convention.

### 12.1 Models-3 I/O API Data Convention

For the Models-3 I/O API, support for Lambert conformal conic (LCC) map projection, Universal Transverse Mercator (UTM) map projection, and polar stereographic map projection was added in VERDI 1.1., and Mercator projection in VERDI 1.2. The grid projections listed on the following website are supported, although not all have been tested: [https://www.cmascenter.org/ioapi/documentation/all\\_versions/html/](https://www.cmascenter.org/ioapi/documentation/all_versions/html/).

Users that need VERDI to support other projections are encouraged to provide small input datasets as attachments to emails to the m3user listserv, or to [github.com/CEMPD/VERDI/issues](https://github.com/CEMPD/VERDI/issues), for testing and to facilitate future development efforts. PDF: (Fig- 77)) or GitHub:[Figure 77](#) through (Fig- 80)) or GitHub:[Figure 80](#) illustrate sample plots generated for datasets with LCC, polar stereographic, Mercator, and UTM map projections, respectively.

Figure 77. CMAQ Lambert Conformal Conic (GDTYP = 2) Map Projection Example Plot

Figure 78. MCIP Polar Stereographic (GDTYP = 6) Map Projection Example Plot

Figure 79. MCIP Mercator (GDTYP = 7) Map Projection Example Plot

Figure 80. SMOKE UTM (GDTYP = 5) Map Projection Example Plot




Figure 77: Lambert Conformal Conic Map Projection Example Plot




Figure 78: Polar Stereographic Map Projection Example Plot




Figure 79: Mercator Map Projection Example Plot




Figure 80: UTM Map Projection Example Plot

```
*****
CAMx
*****
CAMx

Simulation start time/date : 0.    060428    06118
Simulation end time/date   : 0.    060429    06119
Time zone                  : 0
Max timestep (min)         : 15.
Met Input interval (min)   : 60.
Emiss Input interval (min) : 60.
Output interval (min)      : 60.
Grid Projection Type       : LAMBERT
LAMBERT: center lon/lat    : -97.000    40.000
LAMBERT: true latitudes    : 45.000     33.000
Master Grid X/Y Origin     : -2736.000 -2088.000
Master Grid cell size       : 36.000     36.000
Master Grid NCOL NROW NLAY : 148        112          19
```

Figure 81: Example CAMx diagnostic text file

## 12.2 CAMx Gridded Data Convention

The netCDF-java library used in VERDI includes support for CAMx UAM-IV binary files using a preset default projection. CAMx or UAM binary files contain information about the x and y offsets from the center of the projection in meters, but do not contain information about the projection. The projection information is available in separate diagnostic files, which are part of the CAMx output along with the UAM binaries PDF: (Fig- 81)) or GitHub:Figure 81.

Figure 81. Example CAMx diagnostic text file

The netCDF-java library writes the default projection information to a text file in the directory where the CAMx binary (UAM-IV) file is located. You can then review and edit the projection information to make it consistent with the projection specified in the CAMx diagnostic text files. The definitions of the projection parameters used in the camxproj.txt file are defined using Models-3 I/O API format [https://www.cmascenter.org/ioapi/documentation/all\\_versions/html/](https://www.cmascenter.org/ioapi/documentation/all_versions/html/). You must edit the camxproj.txt file to match the grid description information provided in the corresponding camx.diag file. PDF: (Fig- 82)) or GitHub:Figure 82 shows the definition for the grid projection parameters for a Lambert conformal conic projection.

Figure 82. Models-3 I/O API Map Projection Parameters for Lambert Conformal Conic Projection

Figure PDF: (Fig- 83)) or GitHub:Figure 83 shows the values of the camxproj.txt after editing it to match the values of the camx.diag file and using the definitions of the Models-3 grid parameters.

Figure PDF: (Fig- 84)) or GitHub:Figure 84 shows the resulting Tile Plot of the CAMx sample dataset.

Figure 83. Edited Example Projection File: camxproj.txt

**Lambert Conformal Conic:**

```
GDTYP = 2
P_ALP <= P_BET are the two latitudes which determine the projection cone;
P_GAM is the central meridian.
(X_CENT,Y_CENT) are the lat-lon coordinates for the center (0,0) of the
Cartesian coordinate system. Coordinate units are meters.
```

Figure 82: Models-3 I/O API Map Projection Parameters for Lambert Conformal Conic Projection

```
# Projection parameters are based on IOAPI. For details, see
www.baronams.com/products/ioapi/GRIDS.html
GDTYP=2
P_ALP=33.0
P_BET=45.0
P_GAM=-97.0
XCENT=-97.0
YCENT=40.0
```

Figure 83: Edited Example Projection File: camxproj.txt

Figure 84. CAMx Tile Plot




Figure 84: CAMx Tile Plot

### 12.3 WRF netCDF Data Convention

The WRF netCDF data convention is supported in VERDI. <https://www.mmm.ucar.edu/weather-research-and-forecasting-model>

Figure 85. WRF Lambert Conformal (MAP\_PROJ = 1) Plot of Height in Meters on a 1km Texas Domain




Figure 85: WRF Example Plot of Height in Meters on a 1km Texas Domain




Figure 86: MPAS Plot of 2 meter Temperature on World Map

## 12.4 MPAS netCDF Data Convention

The MPAS netCDF data convention is supported in VERDI <https://mpas-dev.github.io/>. A plot of 2 meter Temperature on the World Map PDF is available in: (Fig- 86)) or GitHub:[Figure 86](#) Figure 86. MPAS Example Plot of 2 meter Temperature on World Map

An MPAS Plot of 2 meter temperature zoomed in to California is available PDF: (Fig- 87)) or GitHub:[Figure 87](#)

Figure 87. MPAS Plot of 2 meter Temperature Zoomed in to California




Figure 87: MPAS Plot of 2 meter Temperature Zoomed in to California




Figure 88: MPAS Plot of the 3-d Zonal and Meridional Wind Components and Control Option to Show Wind Vectors

An MPAS plot of the 3-d Zonale and Meridonal Wind components from a daily MPAS-A output file (history file) showing the pull down menu option to select wind vectors is available in PDF: (Figure 88) or GitHub: Figure 88. MPAS Plot of the 3-d Zonal and Meridional Wind components from a daily MPAS-A output file (history file) along with the necessary mesh definition data zoomed into North America. Load the mpas\_UV\_only.2016-07-04.nc file, double click on the “uReconstruct-Meridional” variable, select Tile Plot, then select Controls > Show Wind Vectors. Zoom into an area over North America, or other location to view the wind vectors. Note, the mpas\_UV\_only.2016-07-04.nc file is too large to be distributed with VERDI due to the github 100 Mb file size limit. It may be downloaded from the google drive link: <https://drive.google.com/file/d/1i9aP7s63cz-BRxD6s0AMVsSUeYjRxVIb/view?usp=sharing>




Figure 89: MPAS Plot of the 3-d Zonal and Meridional Wind components from a daily MPAS-A output file (history file) along with the necessary mesh definition data zoomed into North America

The resulting wind vector plot of the 3-d Zonal and Meridional Wind components from a daily MPAS-A output file (history file) along with the necessary mesh definition data zoomed into North America is available in PDF: (Fig- 89)) or GitHub:[Figure 89](#)

Figure 89. MPAS Plot of the 3-d Zonal and Meridional Wind components from a daily MPAS-A output file (history file) along with the necessary mesh definition data zoomed into North America

## 13 Models-3 I/O API Utilities, Data Conversion Programs, and Libraries

As discussed in Section 6.1, routines are available to convert gridded input data to Models-3 I/O API format or new code can be written and contributed to VERDI for use by the community. The Models-3 I/O API routines that have been written to convert data into this format are discussed in this section. If you are unable to use the available routines to convert your data and have a gridded dataset that VERDI is unable to read, please contact VERDI support via the CMAS User Forum <https://forum.cmascenter.org/c/verdi/20> with a description of the dataset.

The Models-3 I/O API Interface contains an extensive set of utility routines. There are example conversion programs to convert data from different data formats into the Models-3 I/O API format. The Models-3 I/O API Utilities are command line programs that are easy to script for automating analysis and post processing. An example of a Models-3 I/O API Utility that may be useful to VERDI users is m3merge. This utility merges selected variables from a set of input files for a specified time period, and writes them to a single output file, with optional variable-renaming in the process. Another utility that you may find useful is m3xtract. This program allows you to extract a few species from a large file and save them to a smaller file on your local computer so you can explore them using VERDI. The Models-3 I/O API Related Programs and Examples can be found at the following web site: [https://www.cmascenter.org/ioapi/documentation/all\\_versions/html/](https://www.cmascenter.org/ioapi/documentation/all_versions/html/).

Airs2m3 is an example of a data conversion program that converts the standard AIRS AMP350 observational data format to the Models-3 I/O API format. The airs2m3 program requires the following inputs:

- The input AIRS AMP350 print format file name.
- The time zone conversion file (provided with the obs2api program - tzt.dat).
- Additional hour shift variable. The AIRS data are hourly averaged, and a 00 time flag represents the hour 00-01. You may wish to represent that data segment by the ending hour. In that case, a 1 should be entered here.
- Starting year, month, day, hour (GMT) (e.g., 1997 07 10 12).
- Ending year, month, day, hour (GMT) (e.g., 1997 07 16 12).
- Name of output variable (8 characters max) (e.g., O3\_OBS).

## 14 Contributing to VERDI Development

If you have made an improvement to VERDI's source code or documentation, please consider contributing it back to the community. You can start by requesting update notifications from VERDI's GitHub site: <https://github.com/CEMPD/VERDI/>.

Instructions on how to set up the Eclipse Development Environment and for running and building VERDI within Eclipse are available in the VERDI Developer Documentation available here: [https://github.com/CEMPD/VERDI/blob/master/doc/Developer\\_Manual/VERDIDevInstructions.md](https://github.com/CEMPD/VERDI/blob/master/doc/Developer_Manual/VERDIDevInstructions.md). If you anticipate doing software development on VERDI, you should contact the members of the VERDI project via <https://forum.cmascenter.org/c/verdi>

VERDI developers will test contributions to the source code and review the applicable documentation changes for inclusion in future VERDI releases. Note that anything you contribute either must have the same license as the rest of VERDI (i.e., GPL) or must be placed in the public domain.

The CMAS Center Forum can be used to query known errors, bugs, suggested enhancements, or submitted code contributions using the following website: <https://forum.cmascenter.org/c/verdi> or the GitHub Issue list <https://github.com/cempd/verdi/issues>. First, search to see if your issue is already listed as a bug or request for enhancement. If you do not see a matching entry, please submit a new topic with your issue to the CMAS Center Forum <https://forum.cmascenter.org/c/verdi>.

## 15 Known Bugs

You are encouraged to review, review the latest release notes: [https://github.com/CEMPD/VERDI/blob/master/doc/Release\\_Notes/README.md](https://github.com/CEMPD/VERDI/blob/master/doc/Release_Notes/README.md) and query the CMAS Forum <https://forum.cmascenter.org/c/verdi/20> to search questions and answers, bug reports, and suggestions. Once a bug is identified through the CMAS User Forum, it will be added as an issue on the Github for the developers to prioritize and fix. <https://github.com/CEMPD/VERDI/issues>.

## 16 Mathematical Functions

All VERDI visualizations are the result of a formula evaluation. Formulas operate on the variables provided by the datasets. The simplest valid formula consists of a single variable; for example, “O3[1]” is the parameter O3 from current dataset 1. Using infix notation, you can construct more complicated formulas using the mathematical operators and functions listed below. (Note that the documentation below derives from the equivalent documentation for the Package for Analysis and Visualization of Environmental data [PAVE], which is available at [http://www.ie.unc.edu/cempd/EDSS/pave\\_doc/EntirePaveManual.html](http://www.ie.unc.edu/cempd/EDSS/pave_doc/EntirePaveManual.html).)

Note that the Batch Script method does not support all of the mathematical functions that are supported within the VERDI GUI and/or the command line script options.

Listed in order of precedence, the functions and operators are:

1. abs, sqr, sqrt, exp, log, ln, sin, cos, tan, sind, cosd, tand, mean, sum, min, max
2. \*\* (power)
3. /, \*

4. +, -
5. <, <=, >, >=
6. ==, !=
7. &&
8. ||

VERDI also supports the following constants:

1. E 2.7182818284590452354
2. PI 3.14159265358979323846
3. NROWS Number of rows in the formula's currently selected domain
4. NCOLS Number of columns in the formula's currently selected domain
5. NLEVELS Number of levels in the formula's currently selected domain

## 16.1 Unary Functions

Unary functions are passed a single argument. Depending on the argument and the function type, the function returns a single value or a matrix of data by performing the function on each cell of the arguments array. For example:

- **sqrt(4):** Returns 2.0.
- **sqrt(O3[1]):** Returns a matrix containing the square root of each value in the O3[1] variable's array.

The following functions return a matrix when passed a dataset variable:

- **abs:** Returns the absolute value of the argument
- **sqrt:** Returns the square root of the argument.
- **sqr:** Returns the square of the argument.
- **log:** Returns the base 10 logarithm of the argument.
- **exp:** Returns Euler's number raised the power of the argument.
- **ln:** Returns the natural logarithm of the argument.
- **sin:** Returns the sine of the argument. The argument is in **radians**.

- **cos:** Returns the cosine of the argument. The argument is in **radians**.
- **tan:** Returns the tangent of the argument. The argument is in **radians**.
- **sind:** Returns the sine of the argument. The argument is in **degrees**.
- **cosd:** Returns the cosine of the argument. The argument is in **degrees**.
- **tand:** Returns the tangent of the argument. The argument is in **degrees**.

The following functions return a single number in all cases when passed a dataset variable:

- **mean:** Average cell value for all cells in currently selected domain.
- **sum:** Sum of all cell values in currently selected domain.
- **min:** For each cell  $(i,j,k)$  in the currently selected domain, this calculates the minimum value for that cell over the currently selected time steps. In other words, the minimum value in cells  $(i,j,k,\text{tmin..tmax})$ .
- **max:** For each cell  $(i,j,k)$  in the currently selected domain, this calculates the maximum value for that cell over the currently selected time steps. In other words, the maximum value in cells  $(i,j,k,\text{tmin..tmax})$ .

## 16.2 Binary Operators

Binary operators are not passed a value but operate on the operands to their left and right. Typically, they return a matrix of data by performing the operation on each cell of the operand's arrays. If both of the operands are single numbers then these binary operators return a single number. For example:

- **O3[1] \* 2:** multiplies each item in the O3[1] array by 2 and returns the result.
- **O3[1] \* O3[3]:** multiplies each item in the O3[1] array by the corresponding item in the O3[3] array and returns the result. (Note that this assumes that the arrays are of equivalent shape.)
- **3 \* 2:** multiplies 3 by 2.

The binary operators:

- **+** Returns the sum of the operands
- **-** Returns the difference of the operands
- **\*** Returns the product of the operands
- **/** Returns the ratio of the operands
- **\*\*** Returns the left operand raised to the power of the right operand

## 16.3 Boolean Operators

Boolean binary operators return either 1 or 0 in each cell of the resulting matrix. If the operands are single numbers, then a single 1 or 0 is returned. The Boolean binary operators:

- < Returns 1 if the left operand is less than the right operand, else 0
- <= Returns 1 if the left operand is less than or equal to the right operand, else 0
- > Returns 1 if the left operand is greater than the right operand, else 0
- >= Returns 1 if the left operand is greater than or equal to the right operand, else 0
- != Returns 1 if the left operand is not equal to the right operand, else 0
- == Returns 1 if the left operand is equal to the right operand, else 0
- && Returns 1 if both operands are nonzero, else 0
- || Returns 1 if either operand is nonzero, else 0

## 16.4 Time Step Index

A time step index can be specified after a variable name. For example, “O3[1]:0” is the value of the O3[1] variable at the first time step.

# 17 VERDI Batch Script Editor

To open the Script Editor, use File>View Script Editor ([Figure 90](#)). Prior running a batch script, remove all datasets from the dataset list. To remove a dataset, click on each dataset in the dataset panel and press the yellow minus button.

Figure 90. File: View Script Editor

An **Open** popup window will be displayed, click on a sample script file in the VERDI\_2.2/data/scripts directory ([Figure 90](#)).

Figure 91. Open Popup Window

After you select a script file and click Open in the Open popup window, the Script Editor window ([Figure 92](#)), the Batch Script File format consists of two blocks – a Global block and a Task Block. The Global block allows you to specify a set of parameters (such as the file and directory names) on which all other tasks are performed. In this block you can specify any parameters that are used to run any other tasks. If the same parameters are specified with different values in a subsequent Task block, those values will overwrite the values specified in the Global block. One Global Block specifies the common parameters shared by all Task blocks, and multiple task blocks can be defined to specify the type of batch operations that will be performed (e.g., defining formulas and creating plots).




Figure 90: File: View Script Editor





Figure 91: Open Popup Window



The screenshot shows a window titled "Script Editor". The content area contains a multi-line text representation of a batch script. The text starts with a header section describing the language and parameters, followed by specific parameter definitions like f, dir, pattern, etc., and concludes with authorship and date information.

```

#####
# NOTE: Batch Scripting Language
#
# * All parameter/value pairs should be inside one of the two blocks --
#   <Global/> or <Task/>
# * Number of blocks is not limited
# * Only one <Global/> block is recommended. <Global/> blocks should
#   contain different items if use multiple <Global/> blocks
# * Parameter values in <Task/> blocks will override those in <Global/>
# * Currently supported parameters (keys, case insensitive):
#   configFile -- configuration file full path
#   f       -- dataset file path/name
#   dir    -- dataset file folder
#   pattern -- dataset file name pattern
#   gtype  -- plot type (tile, line, bar, vector)
#   vectorTile -- vector plot variables
#   s       -- variable name
#   ts      -- time step
#   titleString -- plot title
#   subdomain -- subdomain xmin ymin xmax ymax
#   subTitle1 -- plot subtitle one
#   subTitle2 -- plot subtitle two
#   saveImage -- image file type (png, jpeg, eps, etc.)
#   imageFile -- image file path/name
#   imageDir  -- image file folder
#   drawGridLines -- draw grid lines on the tile plot if 'yes'
#   imageWidth -- image width
#   imageHeight -- image height
#   unitString -- units
#
#
# Author: IE, UNC at Chapel Hill
# Date: 10/27/2014
# Version: 2
#####

```

Figure 92: Top of Sample Script File of file\_patterns.txt

Unload all datasets before running a batch script within the Script Editor. If any dataset is not unloaded a warning message will pop up see Figure 85. requesting that you close all datasets before running your batch script.

Figure 92. Top of Sample Script File – VERDI\_2.2/data/scripts/file\_patterns.txt appears in the right-hand panel within VERDI. The Batch Scripting Language used for the VERDI Script Editor is described in the header of the sample text format script files.

Figure 93. Bottom of Sample Script File – VERDI\_2.2/data/scripts/tile\_patterns.txt

Figure 94. Script Editor Dataset Warning

The Batch Script File format consists of two blocks – a Global block and a Task Block. The Global block allows you to specify a set of parameters (such as the file and directory names) on which all other tasks are performed. In this block you can specify any parameters that are used to run any other tasks. If the same parameters are specified with different values in a subsequent Task block, those values will overwrite the values specified in the Global block. One Global Block specifies the common parameters shared by all Task blocks, and multiple task blocks can be defined to specify the type of batch operations that will be performed (e.g., defining formulas and creating plots).

The multifiles.txt sample script that is provided as part of the VERDI release demonstrates how to create a tile plot using a mathematical combination of variables. An excerpt of that script is shown below.

<Task> dir=D:\verdi-dist2\data\model f=copy.36k.O3MAX f=CCTM46\_P16.baseO2a.36k.O3MAX

```
#####
<Global>
dir=../../data/model
pattern=*CCTM46*
s=O3[1]
savelImage/jpeg
imageDir=../../data/plots
subTitle1="Test SubTitle 1"
subTitle2="Test SubTitle 2"
</Global>

<Task>
gtype=tile
imageFile=O3_tile
</Task>

<Task>
gtype=line
</Task>
```

Figure 93: Bottom of Sample Script File: file\_patterns.txt




Figure 94: Script Editor Dataset Warning

```
f=another.36k.O3MAX s=O3[1]-O3[2]+O3[3]*2 gtype=tile saveImage/jpeg imageDir=D:\verdi-dist2 imageFile=three_components_36k.O3MAX </Task>
```

The above task specifies the name of three input files. The input files are assigned a number based on the order in which they are specified.

[1]=Copy.36k.O3MAX

[2]=CCTM46\_P16.baseO2a.36k.O3MAX

[3]=another.36k.O3MAX

s=O3[1]-O3[2]+O3[3]\*2 defines a formula that uses variables from the three filenames

This formula takes ozone in file 1 and subtracts the ozone in file 2 and adds two times the ozone in file 3.

The type of plot is specified as a tile plot by setting the parameter *gtype* to tile (i.e., *gtype=tile*).

The image file format is specified by setting the parameter *saveImage* to jpeg (i.e., *saveImage/jpeg*).

The output directory where the images will be stored is specified by setting the parameter *imageDir* (i.e., *imageDir=D:\verdi-dis2*).

The image file name is specified by setting the parameter *imageFile*; *imageFile=three\_components\_36k.O3MAX*.

Use the left mouse button to highlight the task that you would like to run and then click **Run** in the Script Editor window. A popup window then appears to indicate the task ran successfully ([Figure 96](#)). In this example the title and subtitle were obtained from the definition in the global block. Aspects of the plot defined in the global block are used for multiple tasks and are applied even if only a highlighted task is run.

Figure 95. Highlight Text to Select Task and Click Run

If you select Run without highlighting a Text Block, then the entire batch script executes and generates the plots. To edit the batch script, highlight a segment that you would like to copy and use Ctrl-C to copy the text; then click in an area where you want to paste the text and use Ctrl-V to insert the copied text. Test your changes to the script by highlighting the text block and click run. When your script executes successfully VERDI displays the popup window shown in ([Figure 96](#)). If the user has specified an incorrect path, or incorrect filename for the input dataset, then a series of error messages will appear, starting with the message shown in ([Figure 97](#)).

NOTE: Click either the Save or the Save As... button to save your edits before exiting the Script Editor.

After saving the script file (e.g. C:\verdi-script\myscript.txt), you can run the batch script directly from command lines without invoking the VERDI GUI. On a Windows computer, start a command window, navigate to the directory containing your run.bat file, and then run this command:

```
run.bat -batch C:\verdi-script\myscript.txt
```

On Linux/Mac platforms, change directory to where the Verdi.sh is located and execute this command (assuming your script file myscript.txt is saved in /home/user/verdi-script directory):

```
./verdi.sh -batch /home/user/verdi-script/myscript.txt
```

```

<Global>
configFile=../../data/configs/o3_10bin.cfg
dir=../../data/model
pattern=*CCTM46*
s=O3[1]
saveImage=png
imageDir=../../data/plots
subdomain=20 10 75 50
</Global>

#####
# Data files picked #
# up from patterns #
# specified for names #
#####

<Task>
gtype=tile
</Task>

```

Figure 95: Script Editor




Figure 96: Successful Batch Script Run Message

(Note: the full path to the batch script must be specified. Neglecting to provide the full path along with the batch script name generates the following error: No such file or directory.) The batch script usage will also be displayed from the command line after typing the following command:

(Windows)

run.bat –batch

(Linux/Mac)

./verdi.sh –batch

Figure 96. Successful Batch Script Run Message

If the user has specified an incorrect path, or incorrect filename for the input dataset, then a series of error messages will appear, starting with the message shown in (Figure 97).

Figure 97. Unsuccessful Batch Script Run Message




Figure 97: Unsuccessful Batch Script Message: File not found

The VERDI Batch Editor checks to see if the path specified by the user as the imageDir exists. If the path does not exist, VERDI displays the error message:

“java.io.FileNotFoundException: with the path and filename listed”

followed by the message “(No such file or directory).” Verify that you supplied the correct path and filename. The directory specified as the image directory must exist prior to running the batch command. Double-click on the file in the imageDir directory to load and view the image file in your default visualization software. (Figure 98) illustrates the tile plot image that was generated by running the highlighted text block.

Figure 98. Plot Image Generated by Task Block

## 17.1 Specify hour/time step formula in batch script mode

Specify the timestep using the format:

**VARIABLE[dataset number]:timestep.**

The batch script notation used to specify an hour/time step involves specifying the formula then the hour: O3[1]:17 will result in Ozone for hour 17 from a given file in scripting mode (see Figure 99).

The batch script can be used to generate plots of a specific hour or time step using the formula

**s=Variable[dataset#]:hour**

for example:

**s=O3[1]:17 to plot the Temperature in first dataset for hour 17**

Batch Script Example:

**<Global>**

**dir=\$LOCAL\_DIR/verdi\_2.2/data/model/**

**imageDir=\$LOCAL\_DIR/verdi\_2.2/data/images**

**saveImage=jpeg**

**</Global>**

**<Task>**




Figure 98: Plot Image Generated by Task Block




Figure 99: Tile Plot of Ozone at Time step 17, Layer 1

```

gtype=tile
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile= CCTM46_P16.baseO2a.36k.O3MAX.tstep.17
s=O3[1]:17
</Task>

```

Figure 99. Tile Plot of Ozone at Time step 17, Layer 1

## 17.2 Mathematical function capability in batch script mode

This update provides the user the ability to perform mathematical functions in VERDI using the scripting mode. For example, Find maximum over all time steps at each grid cells.

The batch script can be used to generate plots for each mathematical function by using the task block to define each function. The notation used within the task block is:

**s=Formula(Variable[dataset#])**

For example:

**s=max(O3[1])** to plot the Maximum value over all timesteps for each grid cell in the domain.

**s=min(O3[1])** to plot the Minimum value over all timesteps for each grid cell

**s=mean(O3[1])** to plot the Mean value over all timesteps for each grid cell

**s=sum(O3[1])** to plot the Sum of the variable over all timesteps for each grid cell

The mathematical functions operate over all time steps at each grid cell. Examples for the batch script notation and the images produced are provided in the following sections.

### 17.2.1 Batch Script Example: Maximum Ozone – layer 1 ([Figure 100](#))

```
<Global>
dir=$LOCAL_DIR/verdi_2.2/data/model/
gtype=tile
imageDir=$LOCAL_DIR/verdi_2.2/data/images
saveImage=jpeg
</Global>
<Task>
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepmax.layer1
s=max(O3[1])
</Task>
```

Figure 100. Tile Plot of Maximum Ozone (aggregated over 25 time steps)

### 17.2.2 Batch Script Example : Minimum Ozone – layer 1 ([Figure 101](#))

```
<Global>
dir=$LOCAL_DIR/verdi_2.2/data/model/
gtype=tile
imageDir=$LOCAL_DIR/verdi_2.2/data/images
saveImage=jpeg
</Global>
<Task>
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepmin.layer1
```




Figure 100: Tile Plot of Ozone (aggregated over 25 time steps)




Figure 101: Tile Plot of Minimum Ozone (aggregated over 25 time steps)

```
s=min(O3[1])
```

```
</Task>
```

Figure 101. Tile Plot of Min Ozone (aggregated over 25 time steps)

### 17.2.3 Batch Script Example : Mean of Ozone – layer 1 (Figure 102)

```
<Global>
```

```
dir=$LOCAL_DIR/verdi_2.2/data/model/
```

```
gtype=tile
```

```
imageDir=$LOCAL_DIR/verdi_2.2/data/images
```

```
saveImage=jpeg
```

```
</Global>
```

```
<Task>
```




Figure 102: Tile Plot of Mean Ozone (aggregated over 25 time steps)

```
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepmean.layer1
s=mean(O3[1])
</Task>
```

Figure 102. Tile Plot of Mean Ozone (aggregated over 25 time steps)

#### 17.2.4 Batch Script Example : Sum of Ozone – layer 1 (Figure 103)

```
<Global>
dir=$LOCAL_DIR/verdi_2.2/data/model/
gtype=tile
imageDir=$LOCAL_DIR/verdi_2.2/data/images
saveImage=jpeg
```




Figure 103: Tile Plot of Sum Ozone (aggregated over 25 time steps)

```
</Global>
<Task>
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepsum.layer1
s=sum(O3[1])
</Task>
```

Figure 103. Tile Plot of Sum Ozone (aggregated over 25 time steps)

## 18 Command Line Scripting

The commands described in this section can be executed from the command line through either command line arguments or Windows batch files. In Linux, you can edit the verdi.sh script, adding the command options at the end of the last line of the script. If you are using Windows, edit the run.bat

script, again adding the command options at the end of the last line, and submitting the script at the windows command line. An example syntax for all commands follows the format

<command> <command options>

where the “” at the end of the command is optional.

## 18.1 Example Command Line Script for Linux Users

Set an environment variable \$VERDI\_HOME by using

```
setenv VERDI_HOME //home//a_username//VERDI_2.2
```

Where a\_username is your username.

The following script options will read in the file as the first dataset, select O3[1] as the formula from dataset 1, and create a tile plot of the O3[1].

```
./verdi.sh -f$VERDI_HOME/data/model/CCTM46_P16.baseO2a.36k.O3MAX -s "O3[1]" -gtype tile
```


Example script file (Note that quotes (as shown highlighted in red) may be needed around the entire list of parameters” :

### 18.1.1 8hO3 Daily Max Plot

```
#!/bin/csh -f
setenv DIR //home//training//verdi_2.2//data/OBS
../../verdi.sh

"-f $DIR/ACONC_O3_8hr.dmax
-f $DIR/AQS_overlay_2002_07.ncf
-configFile /home/training/config.txt
-s "O3[1]"
-s "O38[2]*1000"
```

Note: Currently, the syntax for the command line script is slightly different than the syntax for the batch script. For example, the batch script method supports requesting a plot of hour 12 using the notation O3[1]:12, but the command line script option requires the variable name and time step be specified independently:



```

run.bat - Notepad

File Edit View

@ECHO OFF

SET BATCHFILE=%~f2

REM Instructions: If your USER_HOME directory is not already set,
REM you can set it here (set USER_HOME=C:\Users\myUserName).
REM Your VERDI log file will be written in the verdi subdirectory.
REM Refer to your VERDI User's Guide for more information.
SET USER_HOME=%USERPROFILE%
set VERDI_USER=%USER_HOME%

set VERDI_HOME=%~dp0
REM Change the following path if you are not using the version of Java installed with VERDI
set JAVADIR=%VERDI_HOME%\jre
%1

REM Do not edit below this line
REM ****
set DVERDI=%CD%

```

Figure 104: Add %1 to the run.bat script

-s “O3[1]”

-ts 12

## 18.2 Example Command Line Script for Windows Users

Edit the run.bat script in the VERDI\_2.2 directory by right clicking on the file and selecting edit.

Add %1 as pictured below, then Save.

Figure 104. Add %1 to run.bat script

The current run.bat in notepad contains a “%1” at the end that allows it to accept input following the run.bat script using the Windows run command. Unfortunately, this command does not accept directory names that have a space them, such as the “Program Files”. If you would like to enter the script command line options after run.bat, please move the data directory to C:\VERDI\data or some other similar location.

Enter the following in the Run command: cmd

When a command line window opens do the following:

cd C:\Program Files\VERDI\_2.2\

run.bat “-f C:\VERDI\data\model\CCTM46\_P16.baseO2a.36k.O3MAX -s O3[1] -gtype tile”

The other option is to place the script commands within the run.bat itself. Remove the “%1” statement at the end of the run.bat that is provided in the distribution, and add the script options that you would like to use. The following run.bat contains script options that will read in the file C:\VERDI\_2.2\data\model\CCTM46\_P16.baseO2a.36k.O3MAX, select O3[1] as the formula, and create a Tile plot. The changes that you need to make to the run.bat are highlighted in red.




Figure 105: Location of the run.bat script

```
cd .\plugins\bootstrap
SET JAVA=..\..\jre1.6.0\bin\java

%JAVA% -Xmx512M -classpath "./bootstrap.jar;./lib/saf.core.runtime.jar;
./lib/commons-logging.jar;./lib//jpf-boot.jar;./lib//jpf.jar;
./lib\\log4j-1.2.13.jar"
saf.core.runtime.Boot -f C:\\VERDI_2.2\\data\\model\\CCTM46_P16.base02a.36k.03MAX
-s 03[1] -gtype fasttile
```

Run the run.bat script by clicking on Start, then selecting Run, then either using Browse to find the run.bat or typing it in.

Figure 105. Location of the run.bat script

Submit run.bat script from the Run command.

Script commands that can be used for command line scripting (listed in alphabetical order) are described below. Adding support for these script commands in the Script Editor is planned for a future VERDI release.

**[-alias <aliasname=definition>]** defines an alias. You can define an alias by creating a definition using variable names and derived variables that are calculated using the mathematical operators described in Section 15: Mathematical Functions. The alias definition does not include the dataset name. The alias is treated like any other formula once the alias definition and the dataset to which it should be applied are specified. If you need to redefine an alias definition, you must first use the **-unalias** command. The alias definitions are saved to a verdi.alias file in the verdi subdirectory under your home directory. VERDI uses this type of optional file in your home directory to maintain a snapshot of the current aliases being used. The following warning will be reported if an alias is defined more than once: “WARNING: Alias <aliasname> already defined, new definition ignored.” You are also responsible for not making circular references. Use the **-printAlias** command to view what aliases are already defined. Note, you define an alias, VERDI will use that alias if you make a request to plot that variable again. If you are having issues with variable names being redefined, remember to check your verdi.alias file and remove it if needed.

**[-animatedGIF<filename>]** creates an animated GIF by doing an X Window Dump (XWD) of each of the time steps in the tile plot, then converting them to GIF images. If there are many time steps in the dataset, there will be a slight delay before you are again given control of the GUI.

**[-avi<filename>]** saves an animated plot of each of the time steps in the tile plot to the AVI video format.

**[-closeWindow “<windowid>”]** closes the window with the specified window ID.

**[-configFile <configFileName>]** specifies a configuration file for VERDI to use for configuring subsequent tile plots.

**[-copyright]** prints out copyright information for VERDI.

**[-drawDomainTicks ON|OFF]** turns the domain axis ticks on and off.

**[-drawRangeTicks ON|OFF]** turns the range axis ticks on and off.

**[-drawLegendTicks ON|OFF]** turns the ticks in the legend on and off.

**[-drawGridLines ON|OFF]** turns the plot grid lines on and off.

**[-f [[host:]<filename>]** tells VERDI to load in this dataset and make it the currently selected dataset. All datasets will stay in memory.

**[-fulldomain]** sets the VERDI domain matching the currently selected dataset to be completely selected. The currently selected dataset is usually the most recently added dataset.

**[-g <tile|fasttile|line|bar|contour>]** instructs VERDI to create a plot using the specified type and the currently selected formula’s data.

**[-gtype <tile|fasttile|line|bar|contour>]** instructs VERDI to create a plot using the specified type and the currently selected formula’s data (note: tile and fasttile will both generate a fasttile plot starting with VERDI version 1.4).

**[-help|fullhelp|usage]** display the information on all the command line arguments available. Each of these three versions performs the identical function.

**[-legendBins “<bin0,bin1,...,bin\_n>”]** causes VERDI to use the specified numbers as breaks between colors on subsequent plots. The value of this argument is a comma-separated list of numbers. For

example, **-legendBins “1,10,100,1000”** will cause plots to be created with three colors that correspond to values of 1-10, 10-100, and 100-1000. To go back to the default method for determining breaks between bins, enter **-legendBins DEFAULT**.

**[-layer <layer>]** sets the layer range of all formulas to the single level specified.

**[-layerRange <layerMin> <layerMax>]** sets the level range of all formulas to the range specified.

**[-mapName <pathname>/<mapFileName>]** causes VERDI to use the supplied *map name* instead of the default map for tile plots.

**[-openProject <VERDIProjectName>]** opens a previously save VERDI project.

**[-printAlias]** prints existing alias definitions.

**[-project “<VERDIProjectName>”]** save dataset lists and associated formulas as a “project” for later re-use.

**[-quit|exit]** ends the VERDI session.

**[-quicktime]** creates a QuickTime movie of the currently selected plot.

**[-raiseWindow <>windowid>]** raises the window with the specified plot ID (i.e., brings it to the front).

**[-s “<formula>”]** loads the specified formula into VERDI’s memory, and makes it the currently selected formula.

**[-save2ascii “<filename>”]** export data to a tab-delimited data file suitable for reading into a spreadsheet application such as Excel.

**[-saveImage “<image type>” <file name>]** saves the most recently created plot. This command works for all plot types. Supported formats include PNG, BMP, TIF, and JPG.

**[-scatter “<formula1>” “<formula2>”]** creates a scatter plot using the two formulas specified. Note that the formulas for the two components should already have been loaded into VERDI, and they are case sensitive.

**[-showWindow <>windowId> <timestep>]** sets the time step of the window with the specified window ID to the specified time step. The time step must be within the allowable range for the dataset.

**[-subDomain <xmin> <ymin> <xmax> <ymax>]** sets the VERDI domain matching the currently selected dataset to the bounding box specified by its arguments. The currently selected dataset is the most recently added dataset. It is often handy to type **-subdomain** commands into VERDI’s standard input if you are trying to select a very precise subdomain (such as that needed for a vertical cross-section plot).

**[-subTitle1 “<sub title 1 string>”]** allow you to control a plot’s subtitles if desired. Subsequent plots will use the default subtitles, unless these arguments are used again.

**[-subTitle2“<sub title 2 string>”]** allow you to control a plot’s subtitles if desired. Subsequent plots will use the default subtitles, unless these arguments are used again.

**[-subTitleFont <fontSize>]** allow you to control the font size of the subtitle of a plot.

**[-system “<system command>”]** sends the specified command to the operating system’s command line.

**[-tfinal <final time step>]** sets the last time step for each formula's time-step range to the specified step number, where the first step number is denoted by 1.

**[-tinit <initial time step>]** sets the first time step for each formula's time-step range to the specified step number, where the first step number is denoted by 1.

**[-titleFont <fontSize>]** allows you to control the font size of the title of a plot.

**[-titleString “<title string>”]** sets the title for the next plot made to the specified title. Subsequent plots will use the default VERDI title, unless this argument is used again. Unicode characters can be used together with text in title string. For example, if you want to display “2.5” as subscripts in PM2.5, you can insert Unicode “2082” for subscripted 2, Unicode “2024” for a dot and Unicode “2085” for subscripted 5, such as **-titleString “PM208220242085”**.

**[-ts <time step>]** sets the selected time step for each formula in VERDI's memory to the specified step number, where the first step number is denoted by 0. This will remain the selected time step until you change it. It affects only tile plots and vertical cross-section plots.

**[-unalias <aliasname>]** is used to undefine an alias.

**[-unitString “<unit string>”]** can be used to override the default unit label used for plots. The default value comes from the dataset(s) themselves.

**[-vector “<U>” “<V>”]** creates a vector plot with U as the left-to-right vector component and V as the down-to-up vector component. There are no background colors used for this type of plot. Note that the formulas for the two components should already have been loaded into VERDI, and they are case sensitive.

**[-vectorTile “<formula>” “<U>” “<V>”]** creates a vector plot with the result of “**formula**” as the background tiles, U as the left-to-right vector component, and V as the down-to-up vector component. Note that the formulas for the three components should already have been loaded into VERDI, and they are case sensitive.

**[-version]** prints out information about the VERDI version being used on the standard output stream.

**[-verticalCrossPlot “X|Y” “<column/row>”]** creates a vertical cross-section plot. You indicate whether this will be an *x* or *y* cross-section plot and what row or column to use as the base.

**[-windowid]** prints the window ID of the currently selected plot.

## 19 Areal Interpolation Calculations

Before calculating the average value for a polygon segment, the area for each polygon is calculated using the projection of the grid system loaded. The system then calculates the area of overlay between each grid cell and the polygon segment.

The total contribution of a value (concentration, deposition, rainfall, etc.) from each cell for a given polygon segment is calculated using the following equation:

TV *i* = sum (Orci \* Vrc) where

Orci = Area of overlay of cell at row *r* and column *c* with segment *i*,

$V_{rc}$  = value of cell at row r and column c, and  
r and c iterate across the rows and columns of the grid.

The Average Value is calculated by dividing the total value by the area of the polygon segment:

$$\text{Average } V_i = \frac{\sum V_{rc}}{\sum A_i} \text{ where}$$

$$A_i = \text{Area of the polygon segment } i$$

## 20 Visualize Fine Scale Model Outputs

Data from fine scale (neighborhood, or street level) model can be visualized on the street-level maps in VERDI. Given user can provide fine scale map GIS layers (shapefiles) to be loaded into VERDI. Here is a step by step example:

Step 1: Open VERDI GUI and load your fine scale model gridded datasets. you can get access to some sample model files under the folder: VERDI/data/model/wrfout\_d01\_2018-T2-05-20\_00\_00\_00

Step 2: Select variable “T2” and create a “tile plot”. To turn on USA States lines and turn off the USA County lines, click on GIS Layers → Add Map Layers, then check the box in front of “USA States” and go back in again to uncheck the box in front of “USA Counties”.

Figure showing Tile plot of Fine Scale Gridded Dataset: (Fig- 106)) or GitHub:[Figure 106](#).

Figure 106. Tile Plot of Fine Scale Gridded Dataset




Figure 106: VERDI GIS Layers UI




Figure 107: Add Fine Scale GIS Layer using the pop-up window to load other GIS Layers UI

Step 3: Unzip the fine scale shapefile layer provided under VERDI\_2.2/data/

Step 4: To add this or other fine scale GIS layers, click on GIS Layers → Add Map Layers → Other... A pop-up file browser window will show up for you to navigate to the street-level shapefiles, click on “open”.

Figure to add Fine Scale GIS Layer using the pop-up window to load other GIS Layers UI: (Fig- 107) or GitHub:[Figure 107](#).

Figure 107. Add Fine Scale GIS layer




Figure 108: The tile plot with NYC street centerlines

Step 5: Wait for a few seconds until the GIS layers are added to the tile plot, then zoom into your area of interest and explore. The sample shapefiles are used to create the following map can be found at VERDI/data/DCMStreetCenterLine.zip

A Figure of a tile plot with NYC street centerlines: (Fig- 108)) or GitHub:[Figure 108](#).

Figure 108. Tile Plot with NYC Street Centerlines

## 21 Licenses for JAVA Libraries used by VERDI

VERDI has been developed using a number of open source Java libraries. Table 20-1 contains a list of the jar files or Java libraries that are used by VERDI, a link to where each library may be acquired, a link to the location where the license is referenced by the documentation for each library, as well as a link to each license. The distribution for VERDI contains a sub-directory called licenses. This directory contains a copy of the licenses for the open source Java libraries used by VERDI.

List of Java Libraries	Where to acquire software	Reference to Software License for Software	Link to license or the specific license number
JTS (java topology suite) log4j-1.2.13.jar	<a href="http://sourceforge.net/projects/jts-topo-suite/">http://sourceforge.net/projects/jts-topo-suite/</a> <a href="http://www.unidata.ucar.edu/software/netcdf-java/">http://www.unidata.ucar.edu/software/netcdf-java/</a>	<a href="http://www.vividsolutions.com/JTS/jts_frame.htm">http://www.vividsolutions.com/JTS/jts_frame.htm</a>	<a href="http://www.gnu.org/copyleft/lesser.html">http://www.gnu.org/copyleft/lesser.html</a>
saf.core.runtimes.jar	<a href="http://jar.safr.sourceforge.net">http://jar.safr.sourceforge.net</a>	<a href="http://www.eclipse.org/stp/cf/saf/SAFcore.html">http://www.eclipse.org/stp/cf/saf/SAFcore.html</a>	<a href="http://logging.apache.org/log4j/1.2/license.html">http://logging.apache.org/log4j/1.2/license.html</a>
vecmath.jar	<a href="http://java3d.dev.java.net/">http://java3d.dev.java.net/</a>	<a href="https://vecmath.dev.java.net/">https://vecmath.dev.java.net/</a>	<a href="http://www.gnu.org/licenses/old-licenses/gpl-2.0.html">http://www.gnu.org/licenses/old-licenses/gpl-2.0.html</a>
geoapi	<a href="http://geoapi.sourceforge.net/">http://geoapi.sourceforge.net/</a>	<a href="http://www.codeplex.com/GeoAPI/license">http://www.codeplex.com/GeoAPI/license</a>	LGPL V2.1, Feb. 1999
Gt2	<a href="http://sourceforge.net/projects/geotools/">http://sourceforge.net/projects/geotools/</a>	<a href="http://docs.codehaus.org/display/GEOTDOC/00+Source+License">http://docs.codehaus.org/display/GEOTDOC/00+Source+License</a>	<a href="http://www.gnu.org/licenses/lgpl-2.1.txt">http://www.gnu.org/licenses/lgpl-2.1.txt</a>
hsqldb	<a href="http://hsqldb.org/">http://hsqldb.org/</a>		<a href="http://hsqldb.org/web/hsqLicense.html">http://hsqldb.org/web/hsqLicense.html</a>
jfreechart	<a href="http://sourceforge.net/projects/jfreechart/">http://sourceforge.net/projects/jfreechart/</a>	<a href="http://developer.vrjuggler.org/browser/trunk/juggler/external/jfreechart/LICENSE.txt?rev=15441">http://developer.vrjuggler.org/browser/trunk/juggler/external/jfreechart/LICENSE.txt?rev=15441</a>	LGPL V2.1, Feb. 1999
jscience	<a href="http://jscience.org/">http://jscience.org/</a>	<a href="http://swik.net/Jean-Marie-Dautelle">http://swik.net/Jean-Marie-Dautelle</a>	<a href="http://swik.net/License:BSD/BSD+License+Text">http://swik.net/License:BSD/BSD+License+Text</a>
Piccolo 1.2	<a href="http://www.cs.umd.edu/hcil/jazz/">http://www.cs.umd.edu/hcil/jazz/</a>	<a href="http://www.cs.umd.edu/hcil/jazz/download/open-source.shtml">http://www.cs.umd.edu/hcil/jazz/download/open-source.shtml</a>	<a href="http://opensource.org/licenses/bsd-license.php">http://opensource.org/licenses/bsd-license.php</a>
Ucar_ma2	<a href="http://www.unidata.ucar.edu/software/netcdf-java/">http://www.unidata.ucar.edu/software/netcdf-java/</a>	<a href="http://www.unidata.ucar.edu/software/netcdf-java/">http://www.unidata.ucar.edu/software/netcdf-java/</a>	<a href="http://www.gnu.org/copyleft/lesser.html">http://www.gnu.org/copyleft/lesser.html</a>

List of Java Libraries	Where to acquire software	Reference to Software License for Software	Link to license or the specific license number
Repast symphony GIS	<a href="http://repast.sourceforge.net/">http://repast.sourceforge.net/</a>		<a href="http://repast.sourceforge.net/repast-license.html">http://repast.sourceforge.net/repast-license.html</a>
OpenTopoMap	<a href="https://opentopomap.org/about">https://opentopomap.org/about</a>	Kartendaten: © OpenStreetMap-Mitwirkende, SRTM, Kartendarstellung: © OpenTopoMap (CC-BY-SA)	<a href="https://www.openstreetmap.org/copyright">https://www.openstreetmap.org/copyright</a> and <a href="https://creativecommons.org/licenses/by-sa/3.0/">https://creativecommons.org/licenses/by-sa/3.0/</a>

Table - JAVA Libraries used by VERDI

## 22 Acknowledgments

Contributions to VERDI from the community are greatly appreciated.

### 22.1 Data Contributions

#### Sample CAMx Dataset

Marco Rodriguez, CIRA at Colorado State University <http://www.cira.colostate.edu/>

#### Sample Mercator Projection Dataset

Tanya Otte, Atmospheric Modeling and Analysis Division, <http://www.epa.gov/amad/index.html>

### 22.2 Data Reader Contributions

#### I/O Service Provider (IOSP) Interface for CAMx:

Barron Henderson, ORISE Fellow, EPA, Ph.D. student UNC Chapel Hill

#### Incorporating the IOSP into netcdf-java Library:

John Carron, Unidata, <http://www.unidata.ucar.edu/software/netcdf/index.html>

### 22.3 Shapefile Export and High Resolution Background Map Contributions

#### Identifying geolocation issue with shapefile export of gridded data

Michael Geigert, Connecticut Department of Energy and Environmental Protection, [www.ct.gov/deep](http://www.ct.gov/deep)

- [1] Schwede, D., N. Collier, J. Dolph, M.A. Bitz Widing, T. Howe, 2007: A New Tool for Analyzing CMAQ Modeling Results: Visualization Environment for Rich Data Interpretation (VERDI). Proceedings, CMAS 2007 Conference.