InterProcess Communication

A Reference Manual

Reid Simmons • Dale James

Manual Version: August 2011 (updated April 2022)

for IPC Version 3.9.1

Abstract

This manual is a programmer's guide to using the Inter-Process Communication (IPC) library, a platform-independent package for distributed network-based message passing. IPC provides facilities for both publish/subscribe and client/server type communications. It can efficiently pass complicated data structures between different machines, and even between different languages (currently, C/C++, Java, Python and LISP). IPC can run in either centralized-routed mode or direct point-to-point mode. With centralized routing, message traffic can be logged automatically, and there are tools available for visualizing and analyzing the message traffic.

Credits

The IPC was designed by Reid Simmons, a Research Professor in the School of Computer Science at Carnegie Mellon University. It is based on the communications infrastructure used by the Task Control Architecture (TCA), with changes needed to support the NASA New Millennium Program. The primary implementers of TCA were Christopher Fedor, Reid Simmons, and Richard Goodwin, although contributions were made by other members of Reid Simmons' research group. Trey Smith designed and implemented the xdrgen facility (see Appendix B).

Contacts

Questions about IPC, and suggestions for future releases may be addressed to:

Reid Simmons (reids@cs.cmu.edu) Robotics Institute Carnegie Mellon University 5000 Forbes Avenue Pittsburgh PA 15213-3891

If you send a suggestion for the manual, or a correction to it, please be sure to specify the manual version, which is printed on the cover page. If you have a question about IPC, be sure to include the

version number, which is printed when the central server is started.

The IPC mailing list is no longer functional (too much spam). To request to be informed when new IPC versions are created, please send email to reids@cs.cmu.edu..

Obtaining IPC Code

IPC is available via the IPC web page: http://www.cs.cmu.edu/~IPC. The "alpha" release is typically a stable release with the latest features and bug fixes, so feel assured using that version (although back versions are also available). The download contains the latest version of this manual, the IPC source code, installation instructions for most supported operating systems, the Comview visualization tool (has not been updated in many years), and the xdrgen tool for generating IPC format strings. In addition, the web site contains background information on IPC.

You can also retrieve IPC via anonymous ftp. Login to ftp.cs.cmu.edu as "anonymous" and use your email address as the password. "cd" to "project/TCA". That directory contains tarred and compressed copies of the latest IPC releases.

Contents

	Abstract iii				
	Creditsii				
	Contacts				
	Obtaining IPC Codeii				
1	INTRODUCTION1				
	Installing IPC				
2	THE CENTRAL SERVER				
_	Access Control				
3	DEFINING MESSAGE DATA FORMATS6				
5					
	IPC formats for Primitive Data Types 6				
	IPC Formats for Composite Data Types 7				
4	BASIC IPC INTERFACE FUNCTIONS10				
	4.1 Return Type				
	4.2 Describe Detectable Errors				
	4.3 Define a Byte Array10				
	4.4 Variable Length Byte Array10				
	4.5 Message Handler Type10				
	4.6 Message Handler Type for Automatic				
	Unmarshalling10				
	4.7 Handler Type for Non-Message Events11				
	4.8 Handler Type for Connection Notifications1				
	4.9 Handler Type Subscription Notifications11				
	4.10 Describe Level of "Verbosity" for IPC				
	Output				
	4.11 Set Variable to Last Detected Error11				
	4.12 Print Error Message				
	4.14 Connect to IPC Communication Network on				
	a Given Host Machine				
	4.15 Connect to IPC Communication Network .12				
	4.16 Connect to IPC Communication Network				
	without Listening12				
	4.17 Disconnect from IPC Communication				
	Network12				
	4.18 Is the IPC Network Connected12				
	4.19 Is the Named Module Connected12				

	4.20	Register Message with IPC Network13
	4.21	Is the Message Defined13
	4.22	Publish a Message13
	4.23	Publish a Variable Length Message14
	4.24	Publish a Fixed-Length Message14
	4.25	Return Message Name14
	4.26	Subscribe to Specific Message Type14
	4.27	Subscribe to Specific Message Type with
		Automatic Unmarshalling14
	4.28	Unsubscribe to Specific Message Type15
	4.29	Integrate Non-Message Event Handling with
		Message Event Handling15
		Unsubscribe to File-Descriptor Type15
		Get the Open IPC Sockets16
		Listen for Subscribed Events16
		Listen for Queued Subscribed Events16
		Listen for Given Amount of Time16
		Handle One IPC Event16
		Enter Infinite Dispatch Loop17
		Return Message Size17
		Enable Receiving Multiple Messages17
	4.39	Select Level of "Verbosity" for Module
	4.40	Output
		Set Priority for Message Instances
		Set Message Queue Length
		Notify of New Connections
		Notify of New Disconnections
		Unsubscribe to Connection Notifications 18
		Unsubscribe to Disconnection Notifications 18
		Number of Current Subscribers
		Notify of New Subscribers
		Unsubscribe to Subscription Notifications 19
		Shut Down Central Server
	4.50	Shut Down Specific Task19
5	QU]	ERY/RESPONSE20
	5.1	Reply to a Query Message20
	5.2	Enable Replies Outside a Handler20
	5.3	Await Response to a Query21
	5.4	Send a Query and Block Waiting21
	5.5	Respond with a Variable Length Message.21
	5.6	Await a Response with a Variable Length
		Message22

IPC Reference Manual

	5.7	Send a Variable Length Query and Block Waiting22				
6	MA	RSHALLING DATA23				
	6.1	Compile a Format String23				
	6.2	Define a New Format23				
	6.3	Is Format Consistent24				
	6.4	Format Associated with a Message Name.24				
	6.5	Format Associated with a Message Instance24				
	6.6	Converting Data Structures to Byte Arrays24				
	6.7	Converting Byte Arrays to Data Structures25				
	6.8	Unmarshalling a Pre-Allocated Data				
		Structure25				
		Free up a Byte Array26				
		Free the Data Pointer26				
		Free the Elements of the Structure26				
		Marshall a Structure and Publish a Message27				
		Combine Marshalling and Response27				
		Combine Marshall and Query27				
		Combine Marshall, Query, and Response .28				
		Write a Textual Representation of The Data28				
		Force Data Structure to be an Array28				
		Automatic Data Unmarshalling				
		Associating a Class with Message29				
7		NTEXTS30				
	7.1	Get the Current Context30				
	7.2	Set the Current Context30				
8	TIN	MERS31				
	8.1	Timer Callback Type31				
		Add a Timer31				
	8.3	Add Timer Invoked Once31				
		Add Timer Invoked Periodically32				
		Remove a Timer				
	8.6	Add a Timer by Reference				
	8.7	Remove a Timer by Reference32				
		dix A Example Programs33				
A	Appendix B xdrgen55					
	Purpose of xdrgen55					
	R	unning xdrgen for the first time				
xdrgen command-line options55						
Basic xdrgen type declarations55						

Primitive types	56
Fixed-length arrays	56
Variable-length arrays	56
Enumerated types	57
More about the string type	58
Arbitrary code sections	58
External format definitions	58
Formal XDR language definition	59

IPC Reference Manual

1 INTRODUCTION

The IPC (Inter-Process Communication) software package is designed to facilitate communication between heterogeneous control processes in a large engineered system. An important design principle for the IPC package was that it should provide sufficient functionality and flexibility to meet the needs of real-time autonomous systems, being robust and reliable without weighing the IPC implementation down with unnecessary "bells and whistles." IPC can be used by C, C++, Java, Python and LISP (currently Allegro and Lispworks) processes. It is supported on a number of different machine types (including Sun, SGI, x86, PPC, Rad6000, M68K) and operating systems (SunOS, Solaris, VxWorks, Linux, IRIX, Windows, MacOS).

An IPC-based system consists of an application-independent central server and any number of application-specific processes (see Figure 1). The central server is a repository for system-wide information (such as defined message names), and routes messages and logs message traffic. IPC also supports direct point-to-point communications between processes. The application-specific processes interface with the central server, and with each other, using a linkable library. The interface is the main subject of this manual.

The basic IPC communication package is quite simple: It is essentially a publish/subscribe model, where tasks/processes indicate their interest in receiving messages of a certain type, and when other tasks/processes publish messages, the subscribers all receive a copy of the message. Since message reception is asynchronous, each subscriber provides a callback function (a "handler") that is invoked for each instance of the message type. Tasks/processes can connect to the IPC network, define messages, publish messages, and listen for (and process) instances of messages to which they subscribe.


In addition to IPC message events, tasks/processes can indicate their interest in responding to other events (X window events, keyboard inputs, etc.), where such events can be characterized by input on a C-language "file descriptor" (fd). This provides needed functionality to implement more sophisticated event loops.

IPC also supports a version of the client/server paradigm: sending a directed response to a "query". Both blocking and non-blocking versions of this facility are provided. This facility should be used with caution, as query/response is typically not as safe a way of programming as pure publish/subscribe.

To facilitate passing messages containing complex data structures, IPC provides utilities for marshalling (serializing) a data structure (in any of the supported languages) into a byte stream, suitable for publication as a message, and for unmarshalling a byte stream back into a data structure in the appropriate language by the subscribing handlers. These facilities enable programs to transparently send a wide variety of data formats, including structures that include pointers (strings, variable length arrays, linked lists, etc.) to machines with possibly different byte orderings and packing schemes and to programs running different languages. It is recommended that, rather than sending byte-streams directly, these marshalling/unmarshalling functions be used as they may improve safety of the overall system (by dealing with byte ordering, packing, and non-flat data structures) with only a small penalty in added computation time and memory.

IPC can also be used to invoke a user-specified function at a specific time, or with a specified frequency. These "timer" capabilities enable a module to perform time-critical actions, or to dispatch events at specific times.

The IPC package supports message logging and message data logging. The *Comview* tool (see the Comview Reference Manual) can be used to visualize and analyze patterns of communication. However, the software has not been updated for a number of years, and may no longer work with current compilers/OS.



Installing IPC

For Linux, doing make install in the src dito create central (installed bin/<OS>, where <OS> is an identifier for your operating system) and libipc.a (installed in lib/<OS>). The Java interface to IPC can be created by doing make install in the Java directory, and similarly for Python in the python directory (you will need SWIG in order to make the Python version). To create libraries for LISP, do make USE LISP=1 install in the src directory. In addition, for the Java interface, one needs to add the USE JAVA=1 directive to the make command. In addition, the MAKE SHARED LIBS=1 directive makes shareable libraries (.so and .sa), the THREADED=1 directive makes a thread-safe version of IPC, and the DEBUG=NONE directive makes a version of IPC without debugging symbols.

To run the Python version of IPC, set PYTHONPATH to include both the IPC python and lib/<OS> directories. To run the Java version, set CLASSPATH to include the java/build directory and set LD_LIBRARY_PATH to include the lib/<OS> directory.

For Windows, the src/Windows directory has Visual Studio projects for both central and the IPC library. IPC for Windows has been tested on XP, Vista, and Windows 7.

Finally, the test directory contains a number of test programs (both for Linux – look at the GNUmake-file – and for Windows – look at the test/Windows directory). One suggestion is to start with sizesTest, which tries to ensure that the marshalling functions understand your OS/compiler correctly. If it runs without printing out any error information, you should be able to send any data structure around without problems.

This manual serves as a central information resource for programmers building complex systems. Section 2 describes the central server and the process to start it. Section 3 explains how to describe basic data structures for message passing. Section 4 is a directory of the basic IPC interface function. Section 5 describes query/response functions that IPC provides. Section 6 details the IPC data-

marshalling functions. Sections 0 and 8 describe IPC contexts and timers, respectively. Example programs are provided in the appendix.

2 THE CENTRAL SERVER

IPC uses an application-independent central server module to maintain system-wide information and to route and log message traffic. Before starting any modules, a program named "central" must first be started (Figure 2 lists command line options). The most basic service that the central server provides is message passing. A message sent from any module connected to the server will be forwarded by the server to the module containing the handler for the message (optionally, messages my be sent directly between application modules; see below).

More than one server can run on the same machine, using separate communication ports for each server. Having multiple servers is especially useful for software development – if independent developers must run their IPC servers on the same machine, there is a way to distinguish them.

On machines other than those running VxWorks, one can give commands to the central server while it is running, to display status or change some options.

Modules must first connect to the IPC central server using IPC connect. They then can define messages, together with a description of their data formats, using IPC defineMsg. Modules that want to handle messages must indicate their interest us-IPC subscribeData ing IPC subscribe. Definitions and subscriptions can be done in any order – including subscribing to a message before it is defined. When all messages have been thus registered, modules can publish IPC publishData messages using IPC publish, and the appropriate message handlers will be invoked. Finally, before exiting a module, IPC disconnect should be called, to cleanly disconnect from the network.

The environment variable CENTRALHOST must be set before starting the module. Specify the machine on which the central server is running:

setenv CENTRALHOST lung.learning.cs.cmu.edu

The default TCP socket port is 1381. If the desired server uses a different socket port (i.e., the **-p** option to **central** was used to start the server), the port number must be provided:

setenv CENTRALHOST lung.learning.cs.cmu.edu:1621

Starting a module after making this definition attempts to connect to TCP port 1621 of the host "lung....".

Access Control

[LINUX VERSION ONLY]

You may have an application where it would be beneficial to have the IPC central server be running all the time, but you are hesitant to do so because of possible security holes (e.g., someone from the outside could connect to the IPC port and potentially wreak havoc). To handle this, starting in version 3.7, the IPC central server provides an (optional) capability for access control.

Access control is a layer of network security that automatically denies connections from untrusted hosts, as described by hosts_access (5). In particular, portscanners are denied connections on access-controlled open sockets, and therefore cannot exploit potential bugs in network-level code, either at the user level or the system level. Connections are allowed by consulting the /etc/hosts.allow and /etc/hosts.deny files, where clients listed in hosts.deny but not in hosts.allow are automatically denied access.

Access control can be enabled in IPC by compiling with the ACCESS_CONTROL flag set:

 $\mbox{\%}$ gmake ACCESS_CONTROL=1 install

Note that this only affects the central server.

The access control language is specified fully in the man page hosts_access (5), but in brief, the two files contain lines of the form

daemon : hostname

where hostname can be an IP address or a domain name. The daemon name used by the IPC central server is "central".

For instance, a typical /etc/hosts.deny control file might look like simply:

ALL : ALL

The following are central commands:

help: print this message

display: display the active and pending messages **status**: display the known modules and their status

memory: display total memory usage

close <module>: close a connection to a module
unlock <resource>: unlock a locked resource

The following command line options can also be used as commands:

-v: display server version information

-l<option>: logging onto terminal. Options are:

m (message traffic)

s (status of IPC)

t (time messages are received by central)

d (data associated with messages)

i (ignore logging certain internal messages)

h (handle time summary of incoming messages)

r (log the reference ID as well as the message name)

p (log the reference ID of the message's parent)

x (no logging)

-l (no options) is equivalent to -lmstdh; the default is -lmsi

-L<option>: logging into file.

Options are the same as above, with the addition of

F (don't flush file after each line)

n (don't prompt user for comments)

The default is -Lx

-f<filename>: filename to use for logging; If not specified, name is automatically generated.

-p<port>: connect to central server on this port number.

-c: Use direct (not via central) connections when possible

-I<msgName>: Ignore logging this message (can occur multiple times).

-I<filename>: File with names of messages to ignore logging

-s: silent running; don't print anything to terminal.

-u: don't run the user (tty) interface.

-r: try resending non-completed messages when modules crash and then reconnect.

Figure 2. Starting the Central Server

and /etc/hosts.allow might look like:

central : localhost
sshd : .cs.cmu.edu
sshd-x11 : .cs.cmu.edu

This example denies access to all connections outside the .cs.cmu.edu domain, allows ssh connections inside .cs.cmu.edu, and allows IPC connections only on the local host. For message passing between computers, a second, commaseparated, hostname could be added to the entry for central:

central : localhost, foo.cs.cmu.edu

Remember that the only affected program is central, and so access control only works when IPC connections are central mode, not in direct mode (direct connections are used by starting central with the -c option). However, since *all* IPC modules start by connecting with the central server, even peer-to-peer mode, coupled with access control, is pretty safe.

3 DEFINING MESSAGE DATA FORMATS

This section explains how to describe data structures that will be passed in messages. IPC can send raw byte arrays between processes, but it also provides a powerful data-marshalling facility that enables it to pass data *transparently* between processes, even if the hosts have different byte order or different alignment. To use the facility, one must specify the data formats used by each message. A programmer provides such a structural specification (called a "format string") in parameters to message definition routines. Once this is done, IPC can know how to convert the data structure to a byte stream and how to reconstruct it in the receiving module.

Suppose that the programmer needs to define a message called "SendData." It passes a single integer of data. He would use the following call to define it:

Generally, however, one needs to pass more complicated data structures. Suppose that the message must pass a data structure containing an integer, a character string, and another integer. This call would register the message:

Rather than specifying data formats directly in message registration calls, we recommend first defining a data type, defining a format specifier for that type, and then using the format specifier in the message definition call:

Keeping the type definitions close to the format specifiers ensures that if one needs to make changes to a type, the corresponding definitions can be located and changed quickly. We also recommend that all message names be defined as macros to avoid the possibility of misspelling message names.

As in standard programming languages, IPC format strings are composed of primitive data type specifiers and composite specifiers that enable users to define more complex data types. The following sections describe both of these types of specifiers. Appendix B describes a program called xdrgen that automatically constructs IPC format strings from XDR type definitions.

IPC formats for Primitive Data Types

The previous example used the form "string" to stand for a list of characters. IPC also provides names for other data primitives; some of these names coincide with standard C language types, while others do not. Here is a complete list of primitives:

- char: an 8-bit piece of information, probably an ASCII code; this can be either signed or unsigned.
- byte: any 8-bit piece of information (signed or unsigned);
- short: any 16-bit piece of information (signed or unsigned);
- long: any 32-bit piece of information (signed or unsigned);
- int: 32 bits of information (signed or unsigned);
- float: 32 bits of information;
- double: 64 bits of information:
- Boolean: information that takes on one of two values: TRUE or FALSE. In C, 1 is TRUE and 0 is FALSE; Java uses true and false; Python uses True and False; LISP uses T and NIL. In the rest of the manual, we use Boolean (TRUE and FALSE) as shorthands for the above language-specific values.
- string: A list of characters—in C, this list is terminated by NULL ('\0');

A table of the various IPC formats, their equivalent LISP and C types, and (for C) size in bytes is given

Format Name	LISP Type	С Туре	Bytes
"ubyte"	(unsigned-byte 8)	unsigned char	1
"byte"	(signed-byte 8)	signed char	1
"ushort"	(unsigned-byte 16)	unsigned short	2
"short"	(signed-byte 16)	signed short	2
"uint"	(unsigned-byte 32)	unsigned int	4
"int"	(signed-byte 32)	signed int	4
"ulong"	(unsigned-byte 32)	unsigned long	4
"long"	(signed-byte 32)	signed long	4
"float"	single-float	float	4
"double"	double-float	double	8
"boolean"		int	4

Figure 3. Primitive Data Types: Names and Lengths

in Figure 3. While some computers/compilers use different sizes for primitives (e.g., 64 bit longs), IPC currently supports only those formats listed. Generalizing IPC to handle different sized primitives is being contemplated.

IPC Formats for Composite Data Types

Composite data formats are aggregates of other data types. The supported composites include:

Structures

To describe a C language "struct" to IPC, surround the component data type names with braces, and place commas between them.

Structures can be nested. For example, a pair of DATA_TYPE components could be specified as follows:

```
"{{int, string, int},{int, string, int}}"
```

Unlike the other supported languages, Python does not support structures that have a fixed sequence of attributes. Thus, without further information, the marshalling/unmarshalling functions will not know which components correspond with which portions of the format string. To rectify this, one can define Python classes that have the fields component, which is a tuple of the names (not the types) of each component, in order. In addition, for nested structures or embedded arrays, one can supply a tuple of (<name>, <type>) to provide additional information to help the marshalling functions allocate the correct instances. Subclassing off of IPCdata provides a print function that uses the fields information to format the data structure nicely. For instance:

```
class DATA_TYPE(IPCdata) :
   fields = ('x', 'str', ('y', int))
```

If the _fields information is not provided, IPC names the attributes _f0, _f1, etc.

Fixed-length and Variable-length Arrays

To describe a fixed-length array, use the following form:

```
"[ data_type: n ]" data type is the base type of the array, and n
```

is the array dimension. If the array is multidimensional, separate the dimension numbers by commas, as in the following example:

```
typedef int array[17][42] DATA_TYPE;
#define DATA_FORM "[int:17, 42]"
```

Variable-length arrays are specified as part of a larger structure, which must contain "int" elements specifying dimensions. The notation

```
"<char: 1,2,3>"
```

indicates that a three dimensional array is contained in a larger data structure whose 1st, 2nd, and 3rd elements specify the dimensions of the array.

For example, a two-dimensional variable array of integers can be specified by placing it inside of the following structure:

```
typedef struct {
  int dimension1;
  int dimension2;
  int **variableArray;
} VARIABLE ARRAY TYPE;
```

The appropriate IPC format string would be:

Pointers, Linked Lists, Recursive Data Structures

Pointers are denoted by an asterisk followed by a data format name. If the pointer value is NULL (or NIL in LISP, or None in Python) no data is sent. Otherwise the data is sent and the receiving end creates a pointer to the data. Note that only the data is passed, not the actual pointers, so that structures that share structure or point to themselves (cyclic or doubly linked lists) will not be correctly reconstructed.

The "self pointer" notation, !*, is used in defining linked (or recursive) data formats. IPC will translate

linked data structures into a linear form before sending and then recreate the linked form in the receiving module. IPC routines assume that the end of any linked list is designated by a NULL (or None or NIL) pointer value. Therefore it is important that all linked data structures be NULL terminated so that the data translation routines work correctly.

```
typedef struct _LIST {
  int x;
  struct _LIST *next;
} LIST_TYPE;
#define LIST TYPE FORMAT"{int,!*}"
```

While only C/C++ differentiates between objects and pointers to objects, the pointer format is still useful in Java, Python and LISP as a way of indicating whether data actually exists to be transmitted.

Enumerated Types

There are two forms for specifying an enumerated type. The basic format is "{enum : <maxVal>}", which indicates that the format is an enumerated type whose last element has the value maxVal. For example, the format string for "typedef enum {A, B, C, D} ENUM_TYPE" would be "{enum : 3}", since 3 is the implicit value of D. Similarly, the format for:

typedef enum{E=1,F=2,G=4,H=8} ENUM1_TYPE would be "{enum : 8}". Note that this cannot be used for enumerated types that have negative values — for those types, you need to represent them using "int".

The alternate form for specifying an enumerated type includes the actual values themselves: "{enum <enumVal0>, <enumVal1>, <enumVal2>, ..., <enumValN>}". For example, the format for ENUM TYPE given above would be "{enum A, B, C, D)". There are two advantages of this form of specification: (1) the logs produced by the central server, and the output of IPC printData, will contain the symbolic values of the enumeration, rather than just the integer values; (2) The LISP version will automatically convert the symbolic value to the associated integer (for C), and vice versa. The symbolic value is the upper-case version of <enumVali>, interned into the :KEYWORD package. For instance, a LISP module could send a message containing the atom :B, and a C-language

module would receive the enumerated value "B" (which would have the integer value 1, given the example above). Note that you cannot use the alternate form if the type declaration explicitly sets the enumerated values (e.g., "{enum E, F, G, H}" will not correctly represent ENUM1_TYPE, given above). Python uses integers as enumerated values.

Of course, as with all of the other format specifiers, enumerated formats can be embedded in more complex format specifications:

```
"{int, {enum A, B, C, D}, [double : 3], {enum : 10}}"
```

Another caveat: The colon (:) is a reserved symbol in the format specification language. You cannot use a colon in any of the enumerated values (same for braces, brackets, commas, and periods).

4 BASIC IPC INTERFACE FUNCTIONS

Types and function prototypes are defined in ipc.h for C users, IPC.java for Java users, IPC.py for Python users, and in ipc.lisp for LISP users. Unless otherwise indicated, all functions are available in all supported languages. The Python and LISP functions are all in the IPC package, and have identical names, arguments, and return types as their C equivalents, except where indicated. The Java functions are also in the IPC package but, for historical reasons, they currently do not have the "IPC_" prefix (it is anticipated that this will change in the near future).

4.1 Return Type

```
typedef enum {
    IPC_Error, IPC_OK, IPC_Timeout
} IPC_RETURN_TYPE
```

Return type for most IPC functions. If the return type is IPC_Error, the cause of the error will be indicated by the variable IPC_erro (4.11).

4.2 Describe Detectable Errors

```
typedef enum {
    IPC_No_Error,
    IPC_Not_Connected,
    IPC_Not_Initialized,
    IPC_Message_Not_Defined,
    IPC_Not_Fixed_Length,
    IPC_Message_Lengths_Differ,
    IPC_Argument_Out_Of_Range,
    IPC_Null_Argument,
    IPC_Illegal_Formatter,
    IPC_Mismatched_Formatter,
    IPC_Wrong_Buffer_Length,
    IPC_Communication_Error
} IPC_ERROR_TYPE
```

Type for describing the different types of errors that IPC can detect.

4.3 Define a Byte Array

```
typedef void *BYTE ARRAY
```

An array of bytes (chars) that is passed around by the IPC communication functions. Not often needed, but for Python, can be created using create-ByteArray(numBytes). Not currently implemented for Java or LISP.

4.4 Variable Length Byte Array

```
typedef struct {
   unsigned int length;
   BYTE_ARRAY content;
}IPC VARCONTENT TYPE,*IPC VARCONTENT PTR
```

Type used to represent a variable length array of bytes. Used to facilitate interfacing between the publish/subscribe functions and the marshalling/unmarshalling functions (Section 6).

For Python, can be created using IPC_VARCONTENT_TYPE() and accessed using vc.length and vc.content. Not currently implemented for Java or LISP.

4.5 Message Handler Type

```
typedef void (*HANDLER_TYPE)

(MSG_INSTANCE msgInstance,

BYTE_ARRAY callData,

void *clientData)
```

The type of message handlers. MSG_INSTANCE is a predefined type that is not accessible to the user (although attributes of it can be accessed – see Section 4.37 and Section 6.5). callData is the content of the message, as sent via a "publish" invocation. clientData is a pointer to any user-defined data, and is associated with the message handler in the "subscribe" call (Section 4.26). Java version currently does not support client data.

4.6 Message Handler Type for Automatic Unmarshalling

The type of message handlers used with IPC_subscribeData (Section 4.27). Similar to HANDLER TYPE (Section 4.5), except that the

second argument is a pointer to the *unmarshalled* content of the message. Java version currently does not support client data.

sage. clientData is a pointer to any user-defined data, and is associated with the handler in the "subscribe" call (see 4.47). Java version currently does not support client data.

4.7 Handler Type for Non-Message Events

The type of handlers for non-message events (e.g., X window events, keyboard input). fd is a Clanguage file descriptor. clientData is a pointer to any user-defined data, and is associated with the message handler in the "subscribe" call. Note that it is the responsibility of these types of event handlers to actually read the input that is on the fd file. Java version currently does not support client data. For Python, the fileno() method can be used to get the file descriptor from a Python file object.

4.8 Handler Type for Connection Notifications

The type of handlers for notification of new modules connecting or disconnecting to the IPC server. moduleName is the name of the module that just connected/disconnected. clientData is a pointer to any user-defined data, and is associated with the handler in the "subscribe" call (see 4.42 and 4.43). Java version currently does not support client data.

4.10 Describe Level of "Verbosity" for IPC Output

typedef enum {
 IPC_Silent,
 IPC_Print_Warnings,
 IPC_Print_Errors,
 IPC_Exit_On_Errors
} IPC_VERBOSITY_TYPE

Type for describing the different levels of "verbosity" that IPC supports. IPC Silent produces no output; IPC Print Warnings prints only warning (but not messages; error) IPC Print Errors prints both warning and error messages; IPC Exit On Errors prints warnings, and if an error occurs, prints the error message (using IPC perror, see 4.12) and exits. The default verbosity is IPC Exit On Errors. The verbosity level can be changed with IPC setVerbosity (see 4.39).

4.11 Set Variable to Last Detected Error

IPC ERROR TYPE IPC errno;

Variable set to the last error detected by an IPC function. Possible error values are given in Section 4.2. Initially set to IPC_NO_ERROR. Not currently available through the Java and Python interfaces.

4.9 Handler Type Subscription Notifications

The type of handlers for notification of new subscriptions to messages. msgName is the name of the message that just had a subscriber added to, or removed from, it. numHandlers is the total number of handlers currently subscribed to that mes-

4.12 Print Error Message

void IPC perror (cont char *msg)

This function prints out the message msg to stderr, followed by a textual description of the current error (see also Sections 4.1 and 4.2).

4.13 Initialize IPC Data Structures

IPC RETURN TYPE IPC initialize (void)

After initialization, one can parse format strings, and marshall and unmarshall data, but not define,

subscribe or publish messages (which can only be done after connecting to the network, see 4.14 and 4.15). It is not necessary to call IPC_initialize before calling IPC_connect (4.15), but it is not an error to do so. This function always returns IPC OK.

4.14 Connect to IPC Communication Network on a Given Host Machine

Connect the task/process to the IPC communication network. taskName is used only for message logging purposes, and needs not be unique (although it is preferable to give each task a unique name). Connects to the central server running on the machine named serverName (see Section 2).

If serverName is NULL, use the machine defined by the environment variable CENTRALHOST. If CENTRALHOST is not set, tries to connect to the local machine.

IPC_connectModule returns IPC_OK if a connection is made or the task is already connected. If a connection cannot be made (e.g., if the central server task that manages communications is not responding), IPC_Error is returned and IPC errno is set to IPC Not Connected.

4.15 Connect to IPC Communication Network

Connect the task/process to the IPC communication network. Equivalent to:

IPC_connectModule(taskName, NULL)
(see Section 4.14).

4.16 Connect to IPC Communication Network without Listening

Most IPC modules listen periodically for message traffic (using IPC_dispatch, Section 4.36, or any of the IPC_listen variants, Sections 4.32-4.35). Some modules, though, merely publish and do not listen. In those cases, it is best to use one of the variants of IPC_connect above, to tell IPC that the module will not be listening periodically for incoming messages. This will prevent the *central* process from sending internal messages to the module. It may affect the functionality of point-to-point (direct) message communication, so this should be used only when absolutely necessary.

A warning is printed if a module subscribes to a message (Section 4.26) or file descriptor (Section 4.29) when in the "no listen" condition, since it is likely that the module will not receive incoming communications on a timely basis.

Not currently implemented in Java or LISP.

4.17 Disconnect from IPC Communication Network

IPC_RETURN_TYPE IPC_disconnect (void)

Disconnect the task/process from the IPC communication network. Any messages that the task/process subscribes to are unsubscribed, and the task can no longer listen for messages or events. This function provides tasks with a clean way of shutting down. Always returns IPC_OK (even if the task is not currently connected).

4.18 Is the IPC Network Connected

Boolean IPC isConnected(void)

Determine if the task/process is currently connected to the IPC network (i.e., to the central server).

Returns a Boolean value, which depends on the language being used (see Section 3).

4.19 Is the Named Module Connected

Boolean IPC isModuleConnected

(const char *moduleName)

Determine if the named module is currently connected to the IPC network (i.e., to the central server).

Returns a Boolean value, which depends on the language being used (see Section 3). In addition, the C version returns -1 on error (which can occur if the module invoking the function is not itself currently connected to the IPC server).

The LISP version is currently not implemented.

```
pair of messages "NAV_request_emphemeris" and "NAV_emphemeris"). In such cases, the subscriber to the message (who is also the publisher of the response) typically defines both messages.
```

The function returns IPC_Error if the task is not currently connected to the IPC network (setting IPC_errno to IPC_Not_Connected).

The Java version does not take the length argument (it is always IPC VARIABLE LENGTH).

4.20 Register Message with IPC Network

Register a message with the IPC network. The message is referred to by its msqName. The msqName can be any valid string, although it is preferable (but not required) that it consist of alphanumeric characters, plus "-", " " and "*". Message instances pass arrays of length bytes. length may be the constant IPC VARIABLE LENGTH, in which case each message instance can have a variable length byte array which is published using IPC publish, IPC publishVC, IPC publishData (Section 4.22, Section 4.23, Section 6.12). formatString is used to provide information for use bv the marshalling/unmarshalling functions (Section 6).

A message needs to be defined only once, in just one task/process. Its definition is propagated to all publishing/subscribing tasks (in particular, a module gets message information from the central server the first time it is published or subscribed, and then caches the definition). It is an error to define a message if it already exists and if length and formatString are different from the existing definition.

Typically a message is defined in the task that publishes the message. An exception is for messages that essentially are the "request" portion of a query/response pair of messages (e.g., there may be a

4.21 Is the Message Defined

Determine whether some task/process has registered a message with the name msgName. Returns a Boolean value, which depends on the language being used (see Section 3).

Note that FALSE is also returned if an error occurs. In C, this can be distinguished from "not defined" by checking the value of IPC_errno: It is set to IPC_Not_Connected if the process is not connected to the central server, and is set to IPC Null Argument if msgName is NULL.

4.22 Publish a Message

Publish (broadcast) an instance of the message msgName, sending a copy of the content byte array to all subscribers of that message. length is the number of bytes of the array pointed to by content. This function can be used to publish fixed length messages: either by passing the constant IPC_FIXED_LENGTH as the length argument, or by passing the length provided when the message was defined.

The function returns IPC_Error if the task is not currently connected to the IPC network (setting IPC errno to IPC Not Connected). It also

returns IPC_Error if the message has not been defined (IPC_Message_Not_Defined), if the message is fixed length and the lengths are not equal (IPC_Message_Lengths_Differ), or if the message is variable length and the length argument is

IPC_FIXED_LENGTH (IPC_Not_Fixed_Length).

There is no way for IPC to determine if length matches the actual number of bytes in the byte array.

Not implemented in Java or LISP – use IPC_publishData, instead; implemented in Python, but not really useful.

4.23 Publish a Variable Length Message

Equivalent to:

but, in addition, it returns IPC_Error if varcontent is NULL (setting IPC_errno to IPC_Null_Argument). Not implemented in Java—use IPC publishData, instead.

4.24 Publish a Fixed-Length Message

Equivalent to:

Not implemented in Java or LISP; Implemented in Python, but not really useful.

4.25 Return Message Name

Return the message name of the given instance of the message.

4.26 Subscribe to Specific Message Type

Indicate interest in receiving messages of type msgName. When a message instance of that type is received (Sections 4.22, 4.23, 4.24), the handler function is invoked and passed three arguments: an identifier of the specific message instance, the message content sent in the publish call, and the clientData, which is a pointer to any user-defined data (and which may be NULL). Java version currently does not support client data.

A given task may subscribe to a message before it is defined, and it may subscribe to the same message type multiple times: if the handler is the same as in a previous subscription, the new clientData replaces the old (in which case, a warning message is issued); if the handler differs from all other handlers for that message, it is added as an additional handler. This enables tasks to subscribe to a message for a specific purpose, and then unsubscribe (Section 4.28) after some period of time, without impacting the rest of the task.

The function returns IPC_Error if the task/process is not currently connected to the IPC communication network (IPC Not Connected)

Not implemented in Java – use IPC_subscribeData, instead.

4.27 Subscribe to Specific Message Type with Automatic Unmarshalling

Indicate interest in receiving messages of type msgName. When a message instance of that type is received (Sections 4.22, 4.23, 4.24), the handler function is invoked and passed three arguments: an

identifier of the specific message instance, the unmarshalled message content sent in the publish call, and the clientData, which is a pointer to any user-defined data (and which may be NULL). Java version currently does not support client data.

IPC_subscribeData function behaves identically to IPC_subscribe, except that, when invoked, the handler is passed *unmarshalled* data, rather than a raw byte array. It is still the user's responsibility to free the data (preferably using IPC freeData, Section 6.10).

The Java and Python interfaces enable one to specify the class type of the data that will be received. For Java, this is the required third argument (no clientData argument); For Python, it is an optional fourth argument – if the class is not specified (or None), a structure of type IPCdata will be created.

The function returns IPC_Error if the task/process is not currently connected to the IPC communication network (IPC_Not_Connected)

4.28 Unsubscribe to Specific Message Type

Indicate that the task/process is no longer interested in having the handler invoked on messages of the given type. Note that if a task/process subscribes to multiple handlers for that message, only the specified handler is removed. If handler is NULL, then all handlers for that message type, subscribed to by that task, are removed (thus, that task will no longer receive any messages of that type). It is not an error to unsubscribe a handler that is not currently subscribed. Message instances that have been published, but not received, when the handler is unsubscribed will not be processed by that handler.

The function returns IPC_Error if the task/process is not currently connected to the IPC communication network (IPC Not Connected)

4.29 Integrate Non-Message Event Handling with Message Event Handling

Some tasks/processes need to handle events other than IPC message traffic (e.g., X events, keyboard input, RS232 input from hardware devices). IPC subscribeFD is used to integrate such additional event handling with the IPC message event handling. fd is a C-language file descriptor that can be used in a select system call. clientData is the same as in IPC subscribe (Section 4.26, Java version currently does not support client data). The handler for an fd-event is invoked with the file descriptor that raised the event and the client-Data. Note that the data which is on the file descriptor is *not* read by the IPC – it is up to the handler to read that data, or to handle it in the appropriate manner (e.g., read and parse tty input, invoke <u>a standard X event handler</u> function).

This function always returns IPC_OK. Since it is up to the handler function to determine how to handle input on the file descriptor, it does not make sense for multiple handlers to subscribe to the same fd input. Note that this is contrary to the behavior of IPC_subscribe: IPC_subscribeFD will never have more than one handler per file descriptor. If an additional handler is subscribed for an fd, it will replace the old handler (and old client data).

4.30 Unsubscribe to File-Descriptor Type

Similar to IPC_unsubscribe (Section 4.28), except that the handlers are associated with file descriptor (fd) events, rather than with message types.

The function always returns IPC OK.

4.31 Get the Open IPC Sockets

fd set IPC getConnections (void)

Returns the set of file descriptors that represent all the communication sockets currently open within IPC. This set may change over time as new modules connect to the system or as messages are sent to, or received from, other modules (especially when messages are sent peer-to-peer).

The function returns the empty set (all zeroes) if IPC is not connected.

4.32 Listen for Subscribed Events

Listen for events (messages or other fd events) that have been subscribed to. The appropriate handlers are invoked for each message instance, or other event, received. The function returns IPC Error if the task/process is not currently connected (IPC Not Connected). It returns IPC Timeout if timeoutMSecs pass without the task having received an event. The function returns, with IPC OK, immediately after handling an event. Actually, if several events arrive simultaneously, or several events are waiting when IPC listen is invoked, then they will all be handled before the function returns – but events that arrive after event handling begins will not be handled within that invocation of IPC listen. The predefined constant IPC WAIT FOREVER indicates that the listen call should never time out.

4.33 Listen for Queued Subscribed Events

A message can still be waiting when IPC_listen returns if it arrives while the IPC_listen is handling another message. To ensure that no messages

are in the queue, use IPC_listenClear, which is roughly equivalent to:

```
if (IPC_listen(timeoutMSecs) !=
    IPC_Timeout)
    while (IPC_listen(0) != IPC_Timeout)
```

If the first call to IPC_listen does not time out, the function will continue listening for messages until there are none (note that a timeout of zero milliseconds means to return immediately, unless an event is already waiting). The function returns IPC_Error if the task/process is not currently connected (IPC Not Connected).

4.34 Listen for Given Amount of Time

This function handles messages until at least timeoutMSecs have passed. It is a bit like the UNIX "sleep" function, except that it will handle messages while it waits. It differs from IPC_listenClear in that it will continue to wait the requested time, even if there are no more messages to process.

Note that the function may take longer than timeoutMSecs to return if it is in the middle of processing a message. The function returns IPC_Error if the task/process is not currently connected (IPC Not Connected).

4.35 Handle One IPC Event

Handle a single IPC message or external event. Return after either (a) the message/event was handled or (b) timeoutMSecs have passed.

IPC_Error is returned if the task/process is not currently connected (IPC_Not_Connected). The function returns with IPC_Timeout if timeoutMSecs pass without the task having received an event.

4.36 Enter Infinite Dispatch Loop

IPC_RETURN_TYPE IPC_dispatch (void)

IPC_dispatch is essentially equivalent to:

while (IPC_listen(IPC_WAIT_FOREVER) !=
IPC Error)

It returns (with IPC_Error) only if the task/process is not connected to the IPC network (IPC Not Connected).

4.37 Return Message Size

A message handler receives three arguments: A pointer to the message instance, a byte array of message data, and client data. This function takes as its argument the message instance and returns the number of bytes in the message data (which may be zero or greater). This function may be useful when the message is a variable length message, but the user does not want to (or cannot) unmarshall it into a known data structure.

4.38 Enable Receiving Multiple Messages

When used in the mode in which a central server routes messages, the server by default sends a module only one message at a time. There are situations in which this may produce undesired latencies. IPC_setCapacity can be used to change the default behavior, causing the central server to send up to capacity messages at a time to the module (where they will be queued on the socket until handled).

Warning: capacity should not be set too high, especially if large messages are being sent, as the central server could possibly become blocked if the socket/pipeline to the module becomes full. Typically, a capacity of 2-4 is sufficient for all purposes.

The function returns IPC_Error if the task/process is not currently connected to the IPC

network (IPC_Not_Connected), or if capacity is less than 1 (IPC Argument Out Of Range).

4.39 Select Level of "Verbosity" for Module Output

Set the IPC current "verbosity" level of the module. Affects if, and how, warning and errors are reported. The function returns IPC_Error (with TPC_error set to the value IPC_Argument_Out_Of_Range if verbosity is not a legal value of IPC_VERBOSITY_TYPE (Section 4.10).

4.40 Set Priority for Message Instances

This function sets the priority (an integer value) for all instances of the given message name. The messages are queued, and dispatched, according to priority value. All messages with the same priority value are queued in order of receipt. Messages that have not been explicitly assigned a priority value are assumed to be at the lowest priority.

As of IPC 3.2, this function works both for messages that are queued within IPC central, as well as for messages that are sent directly, with direct module-to-module communications. This function returns an error if priority is less than zero (IPC_Argument_Out_Of_Range) or if IPC is not connected (IPC Not Connected).

4.41 Set Message Queue Length

This function sets the maximum queue length (an integer value) for instances of the given message name. If length messages of the given type are already queued for a module, and a new message of

that type arrives, then the oldest message is discarded in order to maintain the maximum queue length.

This function works for both centrally queued messages and point-to-point messages. Currently, there appears to be a bug if length is zero. This function returns an error if priority is less than one (IPC_Argument_Out_Of_Range) or if IPC is not connected (IPC Not Connected).

4.42 Notify of New Connections

Invoke handler whenever a new module connects to the IPC server. The handler is invoked with the name of the connecting module and the clientData (see 4.8). Note that the handler is invoked only for modules that connect after the subscription – if a module is already connected, no notification is given (you IPC isModuleConnected, Section 4.19, for that purpose). If the function is called with same handler, the old client data is replaced with the new clientData, but the handler is invoked only once per connection. Java version currently does not support client data.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC Not Connected).

4.43 Notify of New Disconnections

Invoke handler whenever a module disconnects from the IPC server (either because the module exited or because it explicitly called IPC_disconnect). The handler is invoked with the name of the connecting module and the clientData (see 4.8). If the function is called with same handler, the old client data is replaced with the new clientData, but the handler is invoked only once per disconnection. Java version currently does not support client data.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC Not Connected).

4.44 Unsubscribe to Connection Notifications

Tells IPC to no longer invoke handler when a new module connects to the IPC server. Note: Does not free the clientData associated with the handler (see 4.42) – that is up to the user.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC Not Connected).

4.45 Unsubscribe to Disconnection Notifications

Tells IPC to no longer invoke handler when a module disconnects from the IPC server. Note: Does not free the clientData associated with the handler (see 4.43) – that is up to the user.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC Not Connected).

4.46 Number of Current Subscribers

Returns the number of handlers currently subscribed to message msgName. The function returns zero (0) if the message is not currently defined.

The function returns -1 on error. The error conditions include if the module is not currently connected to the IPC network (IPC_Not_Connected) or if msgName is null (IPC Null Argument).

4.47 Notify of New Subscribers

Tells IPC to invoke handler whenever the subscription information changes for msgName, that is, whenever some module either subscribes to receive instances of the message, or unsubscribes to the message. The handler is invoked with the name of the message, the total number of handlers currently subscribed for that message, and the user-define clientData (see 4.9, Java version currently does not support client data). Note that the handler is not invoked for any current subscriptions – only for those that are added or removed after this function is invoked. To determine the number of handlers currently subscribed, you can use IPC numHandlers (see 4.46). If the function is called with same handler, the old client data is replaced with the new clientData, but the handler is invoked only once per change in subscription status.

The function returns IPC Error the task/process is not currently connected to the IPC network (IPC Not Connected), if msgName is null (IPC Null Argument), or if the message is currently defined not (IPC Message Not Defined). Note that, in particular, it is not currently possible to use this function on messages that have not been defined (via IPC defineMsg). This is a limitation that may be lifted in the future, especially if any IPC user feels a need for it.

4.48 Unsubscribe to Subscription Notifications

Tells IPC to no longer invoke handler when the subscription information changes for message msgName. Note: Does not free the clientData

associated with the handler (see 4.47) – that is up to the user.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC_Not_Connected), if msgName is null (IPC_Null_Argument), or if the message is not currently defined (IPC_Message_Not_Defined).

4.49 Shut Down Central Server

void killCentral (void)

[VXWORKS VERSION ONLY]

This function, which is meant to be invoked from the VxWorks shell, cleanly shuts down the central server, closing all sockets and file descriptors. This enables the central server to be restarted, without having to reboot the real-time board.

Implementationally, the task id of the central server is saved at startup, and killCentral sends a SIGTERM to that task. The same functionality can be had by using "i" to print a list of active tasks, then doing "kill 0x<taskid>,15" (15 is the value of SIGTERM).

4.50 Shut Down Specific Task

void killModule (char *taskName)

[VXWORKS VERSION ONLY]

This function, which is meant to be invoked from the VxWorks shell, cleanly shuts down the named task, closing all sockets and file descriptors. This tells the central server that the task has disconnected, and enables the task to be restarted without having to reboot the real-time board.

Implementationally, the task id is looked up from the task name, and killModule sends a SIGTERM to that task. The same functionality can be had by using "i" to print a list of active tasks, then doing "kill 0x<taskid>,15" (15 is the value of SIGTERM).

5 QUERY/RESPONSE

While there is evidence that pure event-driven (publish/subscribe) systems are more reliable and maintainable than those that include query/response (client/server), it is also difficult to restructure existing code to fit this paradigm. Thus, the IPC contains functions for query/response, but it is recommended that they be used with caution (in particular IPC_queryResponse, the blocking form of query/response).

5.1 Reply to a Query Message

Similar to IPC_publish, except that it sends the message msgName directly to the task that sent the message represented by msgInstance (where msgInstance is the first argument of a message handler). The receiving task should be expecting a response by having invoked IPC_queryNotify or IPC_queryResponse. Note that IPC_respond will not trigger any other handlers that subscribe to that message type, either in the same task or different tasks.

For example, suppose task "A" includes the following code:

and suppose task "B" includes subscribes the following handler to receive message "bar":

When task "A" publishes "bar" (via IPC_queryNotify), barHandler will be invoked in task "B" (via IPC dispatch or

IPC_listen). Task "B" responds to the request by computing some result (function bar1), and sending a directed response back to task "A". In task "A", only the fooResponse handler will be invoked – the fooHandler function will *not* be invoked in this situation, even though it subscribes to "foo" messages, in general.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC_Not_Connected). It returns IPC_Error if the message has not been defined (IPC_Message_Not_Defined), if the message is fixed length and the lengths are not equal (IPC_Message_Lengths_Differ), or if the message is variable length and the length argument is IPC_FIXED_LENGTH (IPC_Not_Fixed_Length).

Not implemented in Java — use IPC respondData, instead.

5.2 Enable Replies Outside a Handler

Typically, IPC considers a message has been completed when a handler returns. In particular, the message instance passed to that handler is reclaimed. Occasionally, one needs to respond to a query message outside of the handler – for instance, a query handler might set up something to monitor a piece of hardware and return a result when it becomes available.

To prevent IPC from assuming that the message is completed, one should invoke this function before exiting the handler. In this way, when IPC_respond (Section 5.1) is invoked with that message instance, IPC will consider the message completed and reclaim the message instance.

The function returns IPC_Error if the message instance is NULL or invalid (IPC Null Argument).

5.3 Await Response to a Query

Set up the handler to await the response to the (query) message msgName. Assumes that the receiver of msgName will use a call to IPC_respond to direct the response. The handler is invoked exactly as any other message handler – with the message instance identifier, call data, and client data. Java version currently does not support client data.

This function is *non-blocking*. The handler is invoked asynchronously, from within an IPC dispatch or IPC listen invocation.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC_Not_Connected). It returns IPC_Error if the message has not been defined (IPC_Message_Not_Defined), if the message is fixed length and the lengths are not equal (IPC_Message_Lengths_Differ), or if the message is variable length and the length argument is

IPC_FIXED_LENGTH (IPC_Not_Fixed_Length).

Not implemented in Java – use IPC queryNotifyData, instead.

5.4 Send a Query and Block Waiting

Sends the (query) message msgName, and blocks waiting for a response (sent via IPC_respond) to that particular message instance. When the response is received, sets the replyHandle to point to the data contained within the response. Returns IPC_Timeout if the reply has not been received within the specified interval.

Note that although this function is *blocking*, the calling task can still process other messages while it is awaiting the response. Thus, the state of the task/process may change during the time the function is invoked! For this reason, this function should be used with extreme caution – either check the local state when the function returns, or somehow guarantee that the local state you depend on will not be altered by any other message that you could receive during that time.

The function returns IPC_Error if the task/process is not currently connected to the IPC network (IPC_Not_Connected), if the message has not been defined (IPC_Message_Not_Defined), if the message is fixed length and the lengths are not equal (IPC_Message_Lengths_Differ), or if the message is variable length and the length argument is IPC_FIXED_LENGTH (IPC_Not_Fixed_Length).

Not implemented in Java — use IPC_queryResponseData, instead. For Python, the fifth argument (replyHandle) is not used; instead, the function returns a tuple of two values — the reply byte-array and the IPC_RETURN_TYPE value.

5.5 Respond with a Variable Length Message

Equivalent to IPC respond (Section 5.1), except that it uses a pointer to a structure that includes both the length and content of the message data. Designed to facilitate interfacing with the marshalling/unmarshalling functions. In addition to the revalues of IPC respond, it returns IPC Error if varcontent is NULL (IPC Null Argument).

5.6 Await a Response with a Variable Length Message

Equivalent to IPC_queryNotify (Section 5.3), except that it uses a pointer to a structure that includes both the length and content of the message data. Designed to facilitate interfacing with the marshalling/unmarshalling functions. In addition to the return values of IPC_queryNotify, it returns IPC_Error if varcontent is NULL (IPC_Null_Argument). Java version currently does not support client data.

5.7 Send a Variable Length Query and Block Waiting

Equivalent to IPC_queryResponse (Section 5.4), except that it uses a pointer to a structure that includes both the length and content of the message data. Designed to facilitate interfacing with the marshalling/unmarshalling functions. In addition to the return values of IPC_queryResponse, it returns IPC_Error if varcontent is NULL (IPC Null Argument).

6 MARSHALLING DATA

Strictly speaking, these functions are not needed to run the basic IPC. They are included in the IPC API because they provide a powerful interface between the low-level IPC protocols (which deal in byte streams) and higher-level functions (which deal in C, Java, Python, and LISP structures).

It is suggested, for reasons of both safety and ease of use, that these functions be utilized for all messages, as they can correctly deal with byte ordering and packing between machines. In particular, code that uses them does not need to be changed (except for specifying the format string) if the format of the data structure changes. The overhead for using these functions is small, both in time and memory used.

IMPORTANT: In order to deal with inter-machine differences, it is imperative that messages sent using IPC_marshall be handled by calling IPC_unmarshall. Your code should NOT depend in any way on assumptions about the way the marshalling functions transform data structures.

6.1 Compile a Format String

Returns a pointer to a data structure that encodes the format represented textually by formatString, where formatString adheres to the syntax described in Section 3). Returns NULL if the formatString argument is NULL. Sets IPC_errno to IPC_Illegal_Formatter if the syntax of formatString is illegal (and exits if the verbosity is IPC_Exit_On_Errors, see Section 4.10), and sets it to IPC_Not_Initialized if the IPC has not been initialized (see Section 4.13).

6.2 Define a New Format

 Enable users to associate names with format strings, and use the names in other format strings. For example, one could write:

```
IPC_defineFormat
    ("point","{double, double, double}");
IPC_defineFormat
    ("point-array", "[point:5]");
IPC_defineFormat
    ("two-point-arrays",
     "{point-array, point-array}");
```

Without named formatters, the latter would have to be written:

```
"{[{double, double, double}:5],
  [{double, double, double}:5]}"
```

The use of named formatters reduces the chances of mistyping format strings, promotes modularity (if a type definition changes, the format string need be changed in only one place), and promotes understandability, by enabling one to define names for semantic types (e.g.,

```
IPC defineFormat("radians", "double")).
```

It is suggested that you actually use #define's and defconstant's, rather than explicit strings in the calls to IPC defineFormat:

One thing to note: You must be connected to the IPC server before calling IPC_defineFormat. You do not have to define a named format before you use it in another IPC_defineFormat or an IPC_defineMsg call, but it must be defined before it is used (either explicitly or implicitly) in a marshalling or unmarshalling call.

Defined formats propagate among modules, so only one module need define each format (although it is not an error for multiple modules to define a format - if the definitions are inconsistent, the last definition will take precedence).

TPC_Error is returned if the task/process is not currently connected to the IPC network (with IPC_erro being set to IPC_Not_Connected) or if formatName is NULL (IPC_Null_Argument); otherwise IPC_OK is returned.

6.3 Is Format Consistent

Check whether formatString is the same as the format associated with the message msgName. Checks for semantic equality, not just syntactic equality (that is, the format strings don't have to be exactly the same - the question is whether they parse to the same formatter).

Returns IPC OK if the formatString is the same as the format associated with msgName. IPC Error is returned if the formats differ set (IPC errno is IPC Mismatched Formatter). The function also returns IPC Error if the task/process is not the currently connected to **IPC** network (IPC Not Connected), if msgName is NULL (IPC Null Argument), or if the message has defined not (IPC Message Not Defined).

6.4 Format Associated with a Message Name

```
FORMATTER_PTR IPC_msgFormatter (const char *msgName)
```

Return a pointer to a "formatter" that encodes the format string associated with msqName in the IPC defineMsg call. Returns NULL if the message has not been defined, if the format string associated with the message is NULL, or if the format string does not adhere to the format string syntax (Section 3). The way to differentiate these situations is that in the latter case, IPC errno will be set to IPC Illegal Formatter). returns Also NULL and IPC errno sets to IPC Not Initialized if IPC has not been initialized (see Section 4.13). In addition, will exit if the verbosity is IPC Exit On Errors (see Section 4.10).

The message formatter is cached so that, except for the first call, it is very efficient to retrieve.

6.5 Format Associated with a Message Instance

Equivalent to (but more efficient than) IPC_msgFormatter(IPC_msgInstanceNa me (msgInstance)). Included in the IPC API because it is useful in unmarshalling data within a message handler.

6.6 Converting Data Structures to Byte Arrays

"Marshalling" a data structure means converting it to a format (byte array) that is suitable for transmission by the IPC. Based on the formatter data structure, IPC_marshall sets varcontent->content to the marshalled byte array that represents the data structure pointed to by dataptr, and sets varcontent->length to the length of that array. The result can then be used to publish the message.

For example (blithely ignoring errors):

The implementation of IPC_marshall and IPC_unmarshall uses the data formatter facilities (refer to Section 3), which can transform a large variety of structures, in all the supported languages (C, Java, Python, LISP), including structures with pointers (strings, variable length arrays, matrices, linked lists, etc.), taking into account differences in byte ordering and packing between machine types. For example, the format string for the data structure:

```
struct _matrixList {
   float matrix[2][2];
```

```
char *matrixName;
int count;
struct _matrixList *next;
}
is: "{[float:2,2], string, int, *!}".
```

This function returns IPC_Error if IPC has not been initialized (IPC_Not_Initialized), if the formatter is invalid (IPC_Illegal_Formatter) or if varcontent is NULL (IPC_Null_Argument). Otherwise returns IPC_OK.

Note that, in general, there is no way to determine whether the byteArray actually matches the format of the formatter. There may be some specific error conditions that can be detected, and if so, IPC_Error will be returned.

6.7 Converting Byte Arrays to Data Structures

Allocates and fills in a data structure based on the formatter (Section 3) and the byteArray. Sets the dataHandle to the newly created structure (note that the third argument is not simply a pointer, it is a *handle* – a pointer to a pointer). For example, a handler may be written:

The intent is that the result of unmarshalling a byte array produced by the IPC_marshall function

should return an identical data structure, up to pointer equality.

For Java and Python, the dataHandle argument is not used; instead, the Java function (called un-marshallMsgData) returns the newly created structure and the Python function returns a tuple of the structure and the IPC_RETURN_TYPE. In addition, the Java interface enables one to specify the class type of the data that will be created as the third argument to the function. For Python, use the function IPC_msgClass to associate a class type with a message (if the class is not specified, a structure of type IPCdata will be created).

This function returns IPC_Error if IPC has not been initialized (IPC_Not_Initialized), or if the formatter is invalid (IPC_Illegal_Formatter). Otherwise, the function returns IPC_OK.

6.8 Unmarshalling a Pre-Allocated Data Structure

This function is similar to IPC_unmarshall, except that it does not allocate new space for the unmarshalled data, but instead fills in the dataptr pointer. The function assumes that dataptr points to an already allocated data structure (either on the stack or the heap), that is described by the formatter and is dataSize bytes long. In general, it is a bit more efficient than IPC_unmarshall, in that it does less memory allocation and byte copying.

For example, one could write:

Note the call to IPC_freeDataElements in the above example. While IPC does not allocate new space for the top-level data structure (pointed to by dataptr), it will allocate space for substructures that may occur (for instance, if the structure contains pointers or strings). To perform proper memory management, you should be sure to free such allocated memory using IPC_freeDataElements (Section 6.11). While you do not need to do this if you are sure the structure is fixed-size, it does not hurt to always call IPC freeDataElements.

Not implemented in Java. For Python, the dataSize argument is not used and the function takes an optional class type argument (in case the dataPtr argument is None, in which case a new structure is created). The Python function returns a tuple of the new structure and the IPC_RETURN_TYPE.

The function returns IPC Error if IPC has not been initialized (IPC Not Initialized), if formatter is invalid the (IPC Illegal Formatter), if dataPtr is but the formatter (IPC Null Argument), or if dataSize does not match the size as dictated by the formatter (IPC Wrong Buffer Length). Note that, in general, there is no way to determine whether the byteArray actually matches the format of the formatter. There may be some specific error conditions that can be detected, and if so, IPC Error will be returned.

6.9 Free up a Byte Array

 The basic IPC protocols pass around C byte arrays. This function is used to perform memory management by freeing up those byte arrays. This is done automatically in the IPC_xxxData functions. This function should be used in C programs instead of free, since that enables the memory to be reclaimed by IPC and reused.

6.10 Free the Data Pointer

Frees the dataptr, and any substructures it may have, according to the given format. For example, if dataptr were of type "struct _matrixList *" (see Section 6.6), IPC_freeData would free the top-level structure pointed to by dataptr, the matrixName string, and would recursively free each element of the list.

This function is not available in Java, Python, or LISP (it is not needed).

Returns IPC_Error if IPC is not initialized (IPC_Not_Initialized), if the formatter is invalid (IPC_Illegal_Formatter), or if dataptr is NULL but formatter is not (IPC_Null_Argument). Otherwise returns IPC_OK.

6.11 Free the Elements of the Structure

Frees any substructure the dataptr may have, according to the given format. For example, if the dataptr were of type "struct _matrixList *" (see Section 6.6), IPC_freeDataElements would free the matrixName string, and would recursively free each element of the list, but would not free the top-level structure pointed to by dataptr. This function may be useful in conjunction with IPC unmarshallData (Section 6.8).

This function is not available in Java, Python, or LISP (it is not needed).

Returns IPC_Error if IPC is not initialized (IPC_Not_Initialized), if the formatter is invalid (IPC_Illegal_Formatter), or if dataptr is NULL but formatter is not (IPC_Null_Argument). Otherwise returns IPC_OK.

6.12 Marshall a Structure and Publish a Message

Use the formatter associated with the msgName to marshall the structure pointed to by dataptr into a byte array, and publish the message. Combines the marshalling and publish functionality. Roughly equivalent to:

One can subscribe to messages using either IPC_subscribeData or IPC_subscribe. With IPC_subscribeData the data is automatically unmarshalled, so you never need to unmarshall or deal with byte arrays. With IPC_subscribe, you should put the following at the beginning of your handler functions:

```
IPC_unmarshall
  (IPC_msgInstanceFormatter(msgInstance)
   byteArray, (void **) &dataPtr);
IPC_freeByteArray(byteArray);
```

(in the LISP version, there is another alternative – using the macro IPC_defun_handler (Section 6.18).

Returns IPC_Error under all the situations that IPC_marshall (Section 6.6) and IPC_publish (Section 4.22) would return IPC Error.

6.13 Combine Marshalling and Response

Use the formatter associated with the msgName to marshall the structure pointed to by dataptr into a byte array, and respond to the message instance. Combines the marshalling and query/response functionality. Roughly equivalent to:

Returns IPC_Error under all the situations that IPC_marshall (Section 6.6) and IPC_respond (Section 5.1) would return IPC Error.

6.14 Combine Marshall and Query

Use the formatter associated with the msgName to marshall the structure pointed to by dataptr into a byte array, and send a query. Combines the marshalling and query/response functionality. Roughly equivalent to:

Java version currently does not support client data. The Java version takes, instead, a fourth argument that is the class type of the data to be passed to the handler. The Python version has an optional fifth argument that likewise indicates the class type.

Returns IPC_Error under all the situations that IPC_marshall (Section 6.6) and IPC_queryNotify (Section 5.3) would return IPC Error.

6.15 Combine Marshall, Query, and Response

Use the formatter associated with the msgName to marshall the structure pointed to by dataptr into a byte array, send a query, and wait for the response. Unmarshall the response into a data structure, and sets replyData to that value. Combines the marshalling and query/response functionality. Roughly equivalent to:

Neither the Java nor Python versions use the third argument (replyData); instead, both return the data (with the Python version returning a tuple of the reply data and the IPC_RETURN_TYPE value). Instead, the Java version has a required third argument that is the class type of the data to be returned; the Python version has an optional fourth argument (after timeoutMSecs) that is the class type.

Returns IPC_Error under all the situations that IPC_marshall (Section 6.6) and

IPC_queryResponse (Section 5.4) would return IPC Error.

6.16 Write a Textual Representation of The Data

Write on the given stream a (human-readable) textual representation of the dataptr, including any substructures it may have, according to the given formatter. The stream can be an open file or the terminal (stdout or stderr).

This function is included mainly for debugging purposes.

Returns IPC_Error if IPC is not initialized (IPC_Not_Initialized), if the stream is not open for writing, the formatter is invalid (IPC_Illegal_Formatter), or if dataptr is NULL but formatter is not (IPC_Null_Argument). Otherwise returns IPC OK.

6.17 Force Data Structure to be an Array

```
(IPC_defstruct (name) &rest slots)
/LISP ONLY]
```

Has the same syntax as the LISP defstruct construct, but forces the structure to be an array, so that the marshalling/unmarshalling functions can access and set slots of the structure, without having to know the names of its accessory functions. For example:

```
(IPC:IPC_defstruct (sample)
  (i1 0 :type integer)
  (str1 "" :type string)
  (d1 0.0 :type float))
```

6.18 Automatic Data Unmarshalling

```
(IPC_defun_handler name
          (msg-instance lisp-data client-data)
          &rest body)
```

[LISP ONLY]

Has the same syntax as the LISP defun construct, but produces an IPC handler function that automatically unmarshalls the data and creates a LISP data structure for use by the handler. The following are roughly equivalent:

```
(IPC:IPC_defun_handler barHnd
    (msg-ref msg-data client-data)
    (declare (ignore client-data))
    (format T "~a~%" msg-data)
    (IPC_publishData "fooMsg" msg-data))

(defun barHnd
    (msg-ref byte-array client-data)
    (declare (ignore client-data))
    (let (msg-data)
        (IPC_unmarshall
            (IPC_msgInstanceFormatter msg-ref)
            byte-array msg-data)
        (format T "~a~%" msg-data)
        (IPC_publishData "fooMsg" msg-data)
        (IPC_freeByteArray byte-array)))
```

This facility is now largely superceded by use of IPC subscribeData (Section 4.27).

6.19 Associating a Class with Message

```
IPC msgClass(msg-name, class)
```

[PYTHON ONLY]

If you associate a Python class with a message name, then whenever a message of that name gets unmarshalled, IPC will use that class to fill in the slots. That is, the resulting data structure will be an instance of that class.

7 CONTEXTS

There are occasions when a module needs to connect to more than one central server. For instance, if you have two robots with a relatively slow radio link connecting them, it may be desirable for reasons of bandwidth and latency to have a central server residing on each robot. However, if one robot wants to send a message to the other robot, it needs to (temporarily) access the other robot's IPC subnetwork.

The following functions can be used to achieve this. A module/task can call IPC_connectModule multiple times, giving different serverName's each time (Section 4.14). Each call to IPC_connectModule (or IPC_connect) sets up a different *context*, which is essentially a connection to a particular central server, along with all the messages defined by the modules connected to that server.

To use the context mechanism, it is advisable to store all the contexts in global variables. That is, call IPC_getContext immediately after a call to IPC_connectModule, and store the return value. Then, one can call IPC_setContext with the stored context value before sending a message to a module on that context's subnetwork.

For instance, to implement a *bridge* program (one that passes messages from one subnetwork to another), one could use this fragment of code:

```
if (IPC_getContext() != central1)
   printf("Something screwy going on");
IPC_unmarshall(..., &data);
IPC_setContext(central2);
IPC_publishData(MSG1, data);
IPC_freeData(..., data);
...
}
```

Note that this example illustrates that when a message handler is invoked, IPC automatically sets the current context to be that of the subnetwork that sent the message.

7.1 Get the Current Context

IPC CONTEXT PTR IPC getContext (void)

Get the current IPC context, where *context* is a connection to a given central server. Returns NULL if there is no current IPC connection (i.e., either IPC_connectModule or IPC_connect have not been called, or IPC_disconnect has been called).

7.2 Set the Current Context

Set the current IPC context to be context, where *context* is a connection to a given central server. context should be the return value of a previous IPC getContext call.

Returns IPC_Error (IPC_Null_Argument) if context is NULL. Otherwise, returns IPC OK.

8 TIMERS

There are occasions when a module needs to perform some action at a particular time. IPC provides several functions that enable user-specified functions to be invoked at a given point in time, or periodically over a given interval.

While these functions can be used for time-dependent operations, note that they are not truly interrupt driven - they will be invoked only when the module is within some IPC function that is listening for messages (IPC_dispatch, IPC_listen, IPC_listenClear, IPC_queryResponse, IPC queryResponseVC,

IPC_queryResponseData). If the specified time passes while the module is doing some other computation (or is swapped out), the timer function will be invoked at the next available opportunity. Thus, you should not rely on these functions to provide guaranteed real-time response. This also implies that the timer functions are in effect only while the task/process is connected to the IPC network (i.e., all timer functions are "disabled" before calling IPC_connect and after calling IPC_disconnect).

These functions are not currently available for LISP (please contact us if you need this functionality).

8.1 Timer Callback Type

The type of timer callback handlers. clientData is a pointer to any user-defined data, and is associated with the timer in the "add" call (Sections 8.2, 8.3, and 8.4). Note that Java version currently does not support client data. currentTime is the time at which the handler function is invoked; scheduledTime is the time when it was supposed to be invoked (as indicated by the "add" call). scheduledTime may be later than currentTime because timers are invoked only from within IPC functions that are listening for messages (see above).

8.2 Add a Timer

Add a timer, which will periodically invoke the handler function while IPC is running. clientData is passed to the handler routine when it is invoked (Section 8.1). Java version currently does not support client data.

tdelay is the number of milliseconds to wait for, or between, the timer events. The first invocation of the handler is tdelay milliseconds after the timer is "added". Each additional invocation occurs tdelay milliseconds after the previous invocation was begun.

count is the number of invocations before the timer is automatically removed. If count is TRIGGER_FOREVER, then the timer continues indefinitely, or until explicitly removed by the user (Section 8.5).

If a timer already exists that invokes handler, then the new definition replaces the old one (even if the old definition had been running for a while).

Returns IPC_OK if the timer was successfully added. Returns IPC_Error (and sets IPC_erroo appropriately) if the handler is NULL (IPC_Null_Argument), if tdelay is zero (IPC_Argument_Out_Of_Range), or if count is negative (IPC_Argument_Out_Of_Range).

8.3 Add Timer Invoked Once

Shorthand for setting up a timer that triggers just once. Equivalent to:

Java version currently does not support client data.

8.4 Add Timer Invoked Periodically

Shorthand for setting up a timer that triggers forever. Equivalent to:

Java version currently does not support client data.

Returns the same values as IPC_addTimer, under the same error conditions.

8.7 Remove a Timer by Reference

Remove a timer whose reference matches timer-Ref. timerRef is a reference to a timer gotten from a call to IPC_addTimerByRef (Section 8.6).

Returns the same values as IPC_removeTimer (Section 8.5), under the same error conditions.

8.5 Remove a Timer

Remove a timer whose handler function matches handler (there will be at most one such timer existing at any given time).

Returns IPC_Error if the handler is NULL (setting IPC_errno to IPC_Null_Argument). Otherwise, returns IPC_OK (if a timer with the given handler does not currently exist, a warning is issued, but the function still returns IPC_OK).

8.6 Add a Timer by Reference

Same functionality as IPC_addTimer (Section 8.2), except that this function never replaces any current timer, even if it has the same handler and clientData. Instead, the timerRef pointer is set to a reference to the instance of the timer (so that it can be used to remove the timer, see Section 8.7). Note that TIMER_REF is an internal IPC data type, and its elements cannot be accessed by user application code. Java version currently does not support client data.

If timerRef is NULL, then this function works exactly the same as IPC_addTimer (Section 8.2).

Appendix A Example Programs

File "module.h" is a header file that defines various data structures and format strings for message passing between modules.

```
*************
typedef enum { WaitVal, SendVal, ReceiveVal, ListenVal } STATUS ENUM;
typedef struct { int i1;
               STATUS ENUM status;
                double matrix[2][3];
                double d1;
} T1 TYPE, *T1 PTR;
#define T1 NAME "T1"
/* First form of "enum". 3 is the maximum value-i.e., the value of WaitVal */
#define T1 FORMAT "{int, {enum : 3}, [double:2,3], double}"
typedef struct { char *str1;
               int count;
                T1 TYPE *t1; /* Variable length array of type T1 TYPE */
                STATUS ENUM status;
} T2 TYPE, *T2 PTR;
#define T2 NAME "T2"
/* Alternate form of "enum". */
#define T2 FORMAT
     "{string, int, <T1:2>, {enum WaitVal, SendVal, ReceiveVal, ListenVal}}"
typedef int MSG1 TYPE, *MSG1 PTR;
#define MSG1 "message1"
#define MSG1 FORMAT "int"
typedef char *MSG2 TYPE, **MSG2 PTR;
#define MSG2 "message2"
#define MSG2 FORMAT "string"
typedef T1 TYPE QUERY1 TYPE, *QUERY1_PTR;
#define QUERY1 "query1"
#define QUERY1 FORMAT T1 NAME
typedef T2 TYPE RESPONSE1 TYPE, *RESPONSE1 PTR;
#define RESPONSE1 "response1"
#define RESPONSE1 FORMAT T2 NAME
#define MODULE1 NAME "module1"
#define MODULE2 NAME "module2"
#define MODULE3 NAME "module3"
```

File "module1.c" defines a single message handler to print out its data, and a single terminal interface to send out messages and quit the program. It is a test program for IPC that publishes MSG1 and QUERY1, and subscribes to MSG2. It sends MSG1 whenever an "m" is typed at the terminal; sends a QUERY1 whenever an "r" is typed, and quits the program when a "q" is typed. It should be run in conjunction with module2.

```
*****************
#include <stdio.h>
#include <math.h>
#ifndef M PI
#define M PI 3.14159
#endif
#include "ipc/ipc.h"
#include "module.h"
static void msg2Handler (MSG INSTANCE msgRef, BYTE ARRAY callData,
                        void *clientData)
 MSG2 TYPE str1;
 IPC unmarshallData(IPC msgInstanceFormatter(msgRef), callData,
                     &str1, sizeof(str1));
 printf("msg2Handler: Receiving %s (%s) [%s]\n",
 IPC msgInstanceName(msgRef), str1, (char *)clientData);
 IPC freeByteArray(callData);
}
#ifndef VXWORKS
static void stdinHnd (int fd, void *clientData)
 char inputLine[81];
  fgets(inputLine, 80, stdin);
 switch (inputLine[0]) {
   case 'q': case 'Q':
   IPC disconnect();
   exit(0);
 case 'm': case 'M':
    { MSG1 TYPE i1 = 42;
     printf("\n IPC publishData(%s, &i1) [%d]\n", MSG1, i1);
     IPC publishData(MSG1, &i1);
     break;
    }
  case 'r': case 'R':
    { QUERY1 TYPE t1 = \{666, SendVal,
                       \{\{0.0, 1.0, 2.0\}, \{1.0, 2.0, 3.0\}\}, M PI\};
     RESPONSE1 PTR r1Ptr;
     printf("\n IPC queryResponseData(%s, &t1, &r1Ptr, IPC WAIT FOREVER)\n",
            OUERY1);
     IPC queryResponseData(QUERY1, &t1, (void **)&r1Ptr, IPC WAIT FOREVER);
     printf("\n Received response:\n");
     IPC printData(IPC msqFormatter(RESPONSE1), stdout, r1Ptr);
     IPC freeData(IPC msgFormatter(RESPONSE1), r1Ptr);
     break;
 default:
   printf("stdinHnd [%s]: Received %s", (char *)clientData, inputLine);
   fflush(stdout);
  }
#endif
```

```
#if defined(VXWORKS)
#include <sys/times.h>
void module1(void)
#else
void main (void)
#endif
 /* Connect to the central server */
 printf("\nIPC connect(%s)\n", MODULE1 NAME);
 IPC connect(MODULE1 NAME);
 /* Define the named formats that the modules need */
 printf("\nIPC defineFormat(%s, %s)\n", T1 NAME, T1 FORMAT);
 IPC defineFormat(T1 NAME, T1 FORMAT);
 printf("\nIPC_defineFormat(%s, %s)\n", T2 NAME, T2 FORMAT);
 IPC defineFormat(T2 NAME, T2 FORMAT);
  /* Define the messages that this module publishes */
 printf("\nIPC defineMsq(%s, IPC VARIABLE LENGTH, %s)\n", MSG1, MSG1 FORMAT);
 IPC defineMsg(MSG1, IPC VARIABLE LENGTH, MSG1 FORMAT);
 printf("\nIPC defineMsg(%s, IPC VARIABLE LENGTH, %s)\n",
         QUERY1, QUERY1 FORMAT);
 IPC defineMsq(QUERY1, IPC VARIABLE LENGTH, QUERY1 FORMAT);
 /* Subscribe to the messages that this module listens to.
   * NOTE: No need to subscribe to the RESPONSE1 message, since it is a
  * response to a query, not a regular subscription! */
 printf("\nIPC subscribe(%s, msg2Handler, %s)\n", MSG2, MODULE1 NAME);
  IPC subscribe(MSG2, msg2Handler, MODULE1 NAME);
  #ifndef VXWORKS /* Since vxworks does not handle stdin from the terminal,
                     this does not make sense. Instead, send off messages
                     periodically */
  /* Subscribe a handler for tty input.
    Typing "q" will quit the program; Typing "m" will send MSG1;
     Typing "r" will send QUERY1 ("r" for response) */
 printf("\nIPC subscribeFD(%d, stdinHnd, %s)\n", fileno(stdin),
         MODULE1 NAME);
 IPC subscribeFD(fileno(stdin), stdinHnd, MODULE1 NAME);
 printf("\nType 'm' to send %s; Type 'r' to send %s; Type 'q' to quit\n",
         MSG1, QUERY1);
  IPC dispatch();
#else
#define NUM MSGS (10)
#define INTERVAL (5)
   int i;
   printf("\nWill send a message every %d seconds for %d seconds\n",
           INTERVAL, NUM MSGS);
    for (i=1; i<NUM MSGS; i++) {</pre>
     /* Alternate */
     if (i & 1) {
```

```
MSG1 TYPE i1 = 42;
       printf("\n IPC publishData(%s, &i1) [%d]\n", MSG1, i1);
       IPC publishData(MSG1, &i1);
     } else {
       QUERY1 TYPE t1 = \{666, SendVal,
                        \{\{0.0, 1.0, 2.0\}, \{1.0, 2.0, 3.0\}\}, M PI\};
       RESPONSE1 PTR r1Ptr;
       printf("\n IPC queryResponseData(%s, &t1, &r1Ptr, IPC WAIT FOREVER)\n",
              QUERY1);
       IPC queryResponseData(QUERY1, &t1, (void **) &r1Ptr, IPC WAIT FOREVER);
       printf("\n Received response:\n");
       IPC printData(IPC msgFormatter(RESPONSE1), stdout, r1Ptr);
       IPC freeData(IPC msgFormatter(RESPONSE1), r1Ptr);
    /* This works instead of sleep */
    { struct timeval sleep = {INTERVAL, 0};
      select(FD SETSIZE, NULL, NULL, NULL, &sleep);
    }
 }
#endif
 IPC disconnect();
______
```

File "module2.c" provides examples of both a publish/subscribe message handler and a query/response message handler. It receives the messages sent by module1 and responds when appropriate.

This test program for IPC publishes MSG2 and subscribes to MSG1 and QUERY1. It listens for MSG1 and prints out message data. When QUERY1 is received, it publishes MSG2 and responds to the query with RESPONSE1. It exits when "q" is typed at the terminal, and should be run in conjunction with module1.

```
QUERY1 TYPE t1;
 MSG2 TYPE str1 = "Hello, world";
 RESPONSE1 TYPE t2;
 printf("queryHandler: Receiving %s [%s]\n",
         IPC msgInstanceName(msgRef), (char *)clientData);
  /* NOTE: Have to pass a pointer to t1Ptr! */
  IPC unmarshallData(IPC msgInstanceFormatter(msgRef), callData,
                    &t1, sizeof(t1));
 IPC printData(IPC msgInstanceFormatter(msgRef), stdout, &t1);
  /* Publish this message -- all subscribers get it */
  /* NOTE: You need to pass a *pointer* to the string,
     not just the string itself! */
 printf("\n IPC publishData(%s, &str1) [%s]\n", MSG2, str1);
         IPC publishData(MSG2, &str1);
 t2.str1 = str1;
  /* Variable length array of one element */
 t2.t1 = &t1;
 t2.count = 1;
 t2.status = ReceiveVal;
 /* Respond with this message -- only the query handler gets it */
 printf("\n IPC respondData(%#X, %s, &t2)\n", (int)msqRef, RESPONSE1);
 IPC respondData(msgRef, RESPONSE1, &t2);
 IPC freeByteArray(callData);
static void stdinHnd (int fd, void *clientData)
 char inputLine[81];
 fgets(inputLine, 80, stdin);
 switch (inputLine[0]) {
   case 'q': case 'Q':
     IPC disconnect();
     exit(0);
   default:
     printf("stdinHnd [%s]: Received %s", (char *)clientData, inputLine);
     fflush (stdout);
  }
}
#if defined(VXWORKS)
void module2(void)
#else
void main (void)
#endif
 /* Connect to the central server */
```

```
printf("\nIPC connect(%s)\n", MODULE2 NAME);
 IPC connect(MODULE2 NAME);
 /* Define the messages that this module publishes */
 printf("\nIPC defineMsg(%s, IPC VARIABLE LENGTH, %s)\n", MSG2, MSG2 FORMAT);
 IPC defineMsg(MSG2, IPC VARIABLE LENGTH, MSG2 FORMAT);
 printf("\nIPC defineMsg(%s, IPC VARIABLE LENGTH, %s)\n",
         RESPONSE1, RESPONSE1 FORMAT);
 IPC defineMsq(RESPONSE1, IPC VARIABLE LENGTH, RESPONSE1 FORMAT);
 /* Subscribe to the messages that this module listens to. */
 printf("\nIPC subscribe(%s, msg1Handler, %s)\n", MSG1, MODULE2 NAME);
 IPC subscribe (MSG1, msg1Handler, MODULE2 NAME);
 printf("\nIPC subscribe(%s, queryHandler, %s)\n", QUERY1, MODULE2 NAME);
 IPC subscribe (QUERY1, queryHandler, MODULE2 NAME);
#ifndef VXWORKS /* Since vxworks does not handle stdin from the terminal,
                  this does not make sense. */
 /* Subscribe a handler for tty input. Typing "q" will quit the program. */
 printf("\nIPC subscribeFD(%d, stdinHnd, %s)\n", fileno(stdin),
         MODULE2 NAME);
 IPC subscribeFD(fileno(stdin), stdinHnd, MODULE2 NAME);
 printf("\nType 'q' to quit\n");
#endif
 IPC dispatch();
 IPC disconnect();
______
File "module.lisp" is the LISP equivalent of "module.h".
******************
;;; typedef enum { WaitVal, SendVal, ReceiveVal, ListenVal } STATUS ENUM;
(defconstant STATUS ENUM '(:WaitVal :SendVal :ReceiveVal :ListenVal))
(IPC:IPC defstruct (T1)
(i1 0 :type integer)
 (status 0 :type (or integer symbol))
 (matrix NIL :type array)
 (d1 0.0 :type double))
(defconstant T1 NAME "T1")
;;; First form of "enum". 3 is the maximum value -- i.e., the value of WaitVal
(defconstant T1 FORMAT "{int, {enum : 3}, [double:2,3], double}")
(IPC:IPC defstruct (T2)
 (str1 "" :type string)
 (count 0 :type integer)
 (t1 NIL :type array)
 (status :ReceiveVal :type (or integer symbol)))
```

```
(defconstant T2 NAME "T2")
;;; Alternate form of "enum".
(defconstant T2 FORMAT
"{string, int, <T1:2>, {enum WaitVal, SendVal, ReceiveVal, ListenVal}}")
;;; typedef int MSG1 TYPE, *MSG1 PTR
(defconstant MSG1 "message1")
(defconstant MSG1 FORMAT "int")
;;; typedef char *MSG2 TYPE, **MSG2 PTR;
(defconstant MSG2 "message2")
(defconstant MSG2 FORMAT "string")
;;; typedef T1 TYPE QUERY1 TYPE, *QUERY1 PTR;
(defconstant QUERY1 "query1")
(defconstant QUERY1 FORMAT T1 NAME)
;;; typedef T2 TYPE RESPONSE1 TYPE, *RESPONSE1 PTR;
(defconstant RESPONSE1 "response1")
(defconstant RESPONSE1 FORMAT T2 NAME)
(defconstant MODULE1 NAME "module1")
(defconstant MODULE2 NAME "module2")
(defconstant MODULE3 NAME "module3")
______
```

File "module1.lisp" is the LISP equivalent of "module1.c".

It publishes MSG1 and QUERY1 and subscribes to MSG2. It sends MSG1 whenever a "m" is typed at the terminal, send a QUERY1 whenever an "r" is typed, and quits the program when a "q" is typed. It should be run in conjunction with module2.

```
*****************
;;; Load the common file with all the type and name definitions
(load (make-pathname :DIRECTORY (pathname-directory *LOAD-TRUENAME*)
                    :NAME "module.lisp"))
(IPC:IPC defun handler msg2Handler (msgRef lispData clientData)
  (format T "msg2Handler: Receiving ~s (~s) [~s]~%"
         (IPC:IPC msgInstanceName msgRef) lispData clientData))
(defun stdinHnd (fd clientData)
  (declare (ignore fd))
  (let ((inputLine (read-line)))
    (case (aref inputLine 0)
     ((\#/q \#/Q)
      (IPC:IPC disconnect)
      #+ALLEGRO (top-level:do-command "reset") #+LISPWORKS (abort)
     ((\#\m \#\M))
      (format T "~% (IPC publishData ~s ~d)~%" MSG1 42)
      (IPC: IPC publishData MSG1 42))
     ((#\r #\R)
      (let ((t1 (make-T1 :i1 666
                        ;; T1 does not support symbolic enums, so have to
                        ;; use the corresponding integer value
                        :status (position :SendVal STATUS ENUM)
```

```
:matrix (make-array '(2 3)
                                              :element-type 'double-float
                                              :initial-contents
                                              '((0.0d0 1.0d0 2.0d0)
                                                 (1.0d0 2.0d0 3.0d0)))
                                              :d1 pi))
             r1)
          (format T "~% (IPC queryResponseData ~s ~a r1 IPC WAIT FOREVER)~%"
                 QUERY1 t1)
         (IPC:IPC queryResponseData QUERY1 t1 r1 IPC:IPC WAIT FOREVER)
          (format \overline{T} "~% Received response ~a~%" r1)
         ;; (IPC:IPC printData (IPC:IPC msgFormatter RESPONSE1) T r1Ptr)
      (T (format T "stdinHnd [~s]: Received ~s" clientData inputLine)))))
(defun module1 ()
  ;; Connect to the central server
  (format T "~%(IPC connect ~s)~%" MODULE1 NAME)
  (IPC:IPC connect MODULE1 NAME)
  ;; Define the named formats that the modules need
  (format T "~%(IPC defineFormat ~s ~s)~%" T1 NAME T1 FORMAT)
  (IPC:IPC defineFormat T1 NAME T1 FORMAT)
  (format T "~%(IPC defineFormat ~s ~s)~%" T2 NAME T2 FORMAT)
  (IPC:IPC defineFormat T2 NAME T2 FORMAT)
  ;; Define the messages that this module publishes
  (format T "~%(IPC defineMsg ~s IPC VARIABLE LENGTH ~s)~%" MSG1 MSG1 FORMAT)
  (IPC:IPC defineMsg MSG1 IPC:IPC VARIABLE LENGTH MSG1 FORMAT)
  (format T "~%(IPC defineMsg ~s IPC VARIABLE LENGTH ~s)~%"
          QUERY1 QUERY1 FORMAT)
  (IPC:IPC defineMsg QUERY1 IPC:IPC VARIABLE LENGTH QUERY1 FORMAT)
  ;; Subscribe to the messages that this module listens to.
  ;; NOTE: No need to subscribe to the RESPONSE1 message since it is a
  ;; response to a query not a regular subscription!
  (format T "~%(IPC subscribe ~s 'msg2Handler ~s)~%" MSG2 MODULE1 NAME)
  (IPC:IPC subscribe MSG2 'msg2Handler MODULE1 NAME)
  ;; Subscribe a handler for tty input.
  ;; Typing "q" will quit the program; Typing "m" will send MSG1;
  ;; Typing "r" will send QUERY1 ("r" for response)
  ;; NOTE: 0 is the file descriptor number of stdin (the terminal)
  (format T "~%(IPC subscribeFD ~d 'stdinHnd ~s)~%" 0 MODULE1 NAME)
  (IPC:IPC subscribeFD 0 'stdinHnd MODULE1 NAME)
  (format T "~%Type 'm' to send ~s; Type 'r' to send ~s; Type 'q' to quit~%"
          MSG1 OUERY1)
  (IPC: IPC dispatch)
)
```

The file "module2.lisp" is the LISP equivalent of module2.c.

(IPC:IPC connect MODULE2 NAME)

It is a test program for IPC that publishes MSG2, and subscribes to MSG1 and QUERY. It listens for MSG1 and prints out message data. When QUERY1 is received, it publishes MSG1 and responds to the query with RESPONSE1. It exits when 'q' is typed at terminal. module2 should be run in conjunction with module1.

```
******************
;;; Load the common file with all the type and name definitions
(load (make-pathname :DIRECTORY (pathname-directory *LOAD-TRUENAME*)
                     :NAME "module.lisp"))
(IPC:IPC defun handler msglHandler (msgRef msglData clientData)
  (format T "msqlHandler: Receiving ~s (~d) [~s]~%"
         (IPC: IPC msgInstanceName msgRef) msg1Data clientData))
(IPC:IPC defun handler queryHandler (msgRef queryData clientData)
  (declare (ignore clientData))
  (let ((str1 "Hello, world")
         t2)
    (format T "queryHandler: Receiving ~s [~a]~%"
    (IPC:IPC msgInstanceName msgRef) queryData)
    ;; Publish this message -- all subscribers get it
    (format T "~% (IPC publishData ~s, ~s)~%" MSG2 str1)
    (IPC: IPC publishData MSG2 str1)
    (setq t2 (make-T2 :str1 str1
                     ;; Variable length array of one element
                     :t1 (make-array '(1) :initial-contents (list queryData))
                     :count 1
                    ;; T2 supports symbolic enums, so can use keyword directly
                     :status :ReceiveVal))
    ;; Respond with this message -- only the guery handler gets it
    (format T "~% (IPC respondData ~d ~s ~a)~%" msgRef RESPONSE1 t2)
    (IPC:IPC respondData msgRef RESPONSE1 t2)
) )
(defun stdinHnd (fd clientData)
  (declare (ignore fd))
  (let ((inputLine (read-line)))
    (case (aref inputLine 0)
     ((#\q #\Q)
      (IPC:IPC disconnect)
      #+ALLEGRO (top-level:do-command "reset") #+LISPWORKS (abort)
     (T (format T "stdinHnd [~s]: Received ~s" clientData inputLine)))))
(defun module2 ()
  ;; Connect to the central server
  (format T "~%(IPC connect ~s)~%" MODULE2_NAME)
```

```
;; Define the messages that this module publishes
(format T "~%(IPC defineMsg ~s IPC VARIABLE LENGTH ~s)~%" MSG2 MSG2 FORMAT)
(IPC:IPC defineMsg MSG2 IPC:IPC VARIABLE LENGTH MSG2 FORMAT)
(format T "~%(IPC defineMsg ~s IPC VARIABLE LENGTH ~s)~%"
        RESPONSE1 RESPONSE1 FORMAT)
(IPC:IPC defineMsg RESPONSE1 IPC:IPC VARIABLE LENGTH RESPONSE1 FORMAT)
;; Subscribe to the messages that this module listens to.
(format T "~%(IPC subscribe ~s 'msg1Handler ~s)~%" MSG1 MODULE2 NAME)
(IPC:IPC subscribe MSG1 'msg1Handler MODULE2 NAME)
(format T "~%(IPC subscribe ~s 'queryHandler ~s)~%" QUERY1 MODULE2 NAME)
(IPC:IPC subscribe QUERY1 'queryHandler MODULE2 NAME)
;; Subscribe a handler for tty input. Typing "q" will quit the program
(format T "~%(IPC subscribeFD ~d 'stdinHnd ~s)~%" 0 MODULE2 NAME)
(IPC:IPC subscribeFD 0 'stdinHnd MODULE2 NAME)
(format T "~%Type 'q' to quit~%")
(IPC:IPC dispatch)
```

)

File "module.java" is the Java equivalent of "module.h".

```
**************
public class module {
 /* STATUS ENUM */
 protected static final int WaitVal
 protected static final int SendVal = 1;
 protected static final int ReceiveVal = 2;
 protected static final int ListenVal = 3;
 protected static class T1 {
     public int i1;
     public int status; /* STATUS ENUM */
     public double matrix[/*2*/][/*3*/];
     public double d1;
     public String toString () {
     String str = "{" + i1 + "}, "+ Integer.toString(status) +", [";
     for (int i=0; i<matrix.length; i++) {</pre>
         str += "[";
         for (int j=0; j<matrix[i].length; j++) {</pre>
          str += matrix[i][j];
          if (j != matrix[i].length-1) str += ", ";
         str += "]";
         if (i != matrix.length-1) str += ", ";
     str += "]";
     return str +", "+ d1 +"}";
     }
  }
 protected static final String T1 NAME = "T1";
 // First form of "enum". 3 is the maximum value - i.e., the value of WaitVal
 protected static final String T1 FORMAT =
      "{int, {enum : 3}, [double:2,3], double}";
 protected static class T2 {
   public String str1;
   public int count;
   public T1 t1[]; /* Variable length array of type T1 TYPE */
   public int status; /* STATUS ENUM */
   public String toString () {
     String str = \{\" + str1 + \" , " + count + \", ";
     str += "<";
     for (int i = 0; i<count; i++) str += t1[i].toString();
     str += ">, ";
     str += (status == WaitVal ? "WaitVal"
           : status == SendVal ? "SendVal"
           : status == ReceiveVal ? "ReceiveVal"
           : status == ListenVal ? "ListenVal" : Integer.toString(status));
     return str +"]";
    }
```

```
}
protected static final String
                               T2 NAME = "T2";
// Alternate form of "enum".
protected static final String T2 FORMAT =
    "{string, int, <T1:2>, {enum WaitVal, SendVal, ReceiveVal, ListenVal}}";
protected static final String
                                           = "message1";
                               MSG1
                               MSG1 FORMAT = "int";
protected static final String
protected static final String
                               MSG2
                                           = "message2";
protected static final String
                               MSG2 FORMAT = "string";
protected static final String
                              OUERY1
                                             = "query1";
protected static final String
                              QUERY1 FORMAT = T1 NAME;
                                           = "response1";
protected static final String
                              RESPONSE1
protected static final String
                              RESPONSE1 FORMAT = T2 NAME;
protected static final String MODULE1 NAME = "module1";
protected static final String MODULE2 NAME = "module2";
protected static final String MODULE3 NAME = "module3";
```

File "module1.java" is the Java equivalent of "module1.c".

It publishes MSG1 and QUERY1 and subscribes to MSG2. It sends MSG1 whenever a "m" is typed at the terminal, send a QUERY1 whenever an "r" is typed, and quits the program when a "q" is typed. It should be run in conjunction with module2.

```
******************
import ipc.java.*;
public class module1 extends module {
 private static class msg2Handler implements IPC.HANDLER TYPE {
   msg2Handler(String theClientData) { clientData = theClientData; }
   public void handle (IPC.MSG INSTANCE msgRef, Object callData) {
     System.out.println("msg2Handler: Receiving "+
                 IPC.msgInstanceName(msgRef) +" (\""+ callData
                 +"\") ["+ clientData +"]");
   String clientData;
 }
 private static class stdinHnd implements IPC.FD HANDLER TYPE {
   stdinHnd(String theClientData) { clientData = theClientData; }
   public void handle (int fd) {
     try {
     int in = System.in.read();
     if (in == 'q' \mid | in == 'Q') {
       IPC.disconnect();
       System.exit(-1);
     } else if (in == 'm' || in == 'M') {
```

```
int i1 = 42;
     System.out.println("\n IPC.publishData(\""+ MSG1 +"\", "+ i1 +")");
     IPC.publishData(MSG1, i1);
   } else if (in == 'r' || in == 'R') {
     T1 t1 = new T1();
     t1.i1 = 666;
     t1.status = SendVal;
     t1.matrix = new double[][] {{0.0, 1.0, 2.0}, {1.0, 2.0, 3.0}};
     t1.d1 = java.lang.Math.PI;
     System.out.println("\n r1 = IPC.queryResponseData(\""+ QUERY1
                    +"\", "+ t1 +", T2.class, IPC.IPC_WAIT_FOREVER)");
     T2 r1 = (T2) IPC.queryResponseData(QUERY1, t1, T2.class,
                               IPC.IPC WAIT FOREVER);
     System.out.println("\n Received response: "+ r1.toString());
   } else {
     System.out.println("stdinHnd ["+ clientData +"]: Received "+(char)in);
   // Read in any extra bytes
   while (System.in.available() > 0) System.in.read();
   } catch (Exception e) { e.printStackTrace(); }
  String clientData;
}
private static class handlerChangeHnd implements IPC.CHANGE HANDLE TYPE {
   public void handle (String msgName, int num) {
     System.err.println("HANDLER CHANGE: "+ msgName +": "+ num);
    }
}
private static class handlerChangeHnd2 implements IPC.CHANGE HANDLE TYPE {
   public void handle (String msgName, int num) {
     System.err.println("HANDLER CHANGE2: "+ msqName +": "+ num);
}
private static class connect1Hnd implements IPC.CONNECT HANDLE TYPE {
 public void handle (String moduleName) {
    System.err.println("CONNECT1: Connection from "+ moduleName);
    System.err.println("
                                 Confirming connection ("+
                IPC.isModuleConnected(moduleName) +")");
}
private static class connect2Hnd implements IPC.CONNECT HANDLE TYPE {
 public void handle (String moduleName) {
    System.err.println("CONNECT2: Connection from "+ moduleName);
    System.err.println("
                                  Number of handlers: "+
                IPC.numHandlers(MSG1));
  }
}
private static class disconnect1Hnd implements IPC.CONNECT HANDLE TYPE {
 static boolean first = true;
 public void handle (String moduleName) {
   System.err.println("DISCONNECT: "+ moduleName);
```

```
if (first) IPC.unsubscribeConnect(connect1Hnd.class);
   else IPC.unsubscribeConnect(connect2Hnd.class);
   if (first) IPC.unsubscribeHandlerChange(MSG1, handlerChangeHnd2.class);
   else IPC.unsubscribeHandlerChange(MSG1, handlerChangeHnd.class);
   first = false;
}
public static void main (String args[]) throws Exception {
  // Connect to the central server
  System.out.println("\nIPC.connect(\""+ MODULE1 NAME +"\")");
  IPC.connect(MODULE1 NAME);
  IPC.subscribeConnect(new connect1Hnd());
  IPC.subscribeConnect(new connect2Hnd());
  IPC.subscribeDisconnect(new disconnect1Hnd());
  // Define the named formats that the modules need
  System.out.println("\nIPC.defineFormat(\""+ T1 NAME +"\", \""+
                T1 FORMAT +"\")");
  IPC.defineFormat(T1 NAME, T1 FORMAT);
  System.out.println("\nIPC.defineFormat(\""+ T2 NAME +"\", \""+
                T2 FORMAT +"\")");
  IPC.defineFormat(T2 NAME, T2 FORMAT);
  // Define the messages that this module publishes
  System.out.println("\nIPC.defineMsg(\""+ MSG1 +"\", \""+
                MSG1 FORMAT +"\")");
  IPC.defineMsg(MSG1, MSG1 FORMAT);
  IPC.subscribeHandlerChange(MSG1, new handlerChangeHnd());
  IPC.subscribeHandlerChange(MSG1, new handlerChangeHnd2());
  System.out.println("\nIPC.defineMsg(\""+ QUERY1 +"\", \""+
                QUERY1 FORMAT +"\")");
  IPC.defineMsg(QUERY1, QUERY1 FORMAT);
  IPC.subscribeHandlerChange(QUERY1, new handlerChangeHnd());
  // Subscribe to the messages that this module listens to.
  // NOTE: No need to subscribe to the RESPONSE1 message, since it is a
  //
           response to a query, not a regular subscription!
  System.out.println("\nIPC.subscribeData(\""+ MSG2 +"\", new msg2Handler(\""+
                MODULE1 NAME +"\"), String.class)");
  IPC.subscribeData(MSG2, new msg2Handler(MODULE1 NAME), String.class);
  // Subscribe a handler for tty input.
       Typing "q" will quit the program; Typing "m" will send MSG1;
       Typing "r" will send QUERY1 ("r" for response)
  System.out.println("\nIPC subscribeFD(0, new stdinHnd(\""+
                MODULE1 NAME +"\"))");
  IPC.subscribeFD(0, new stdinHnd(MODULE1_NAME));
  System.out.println("\nType 'm' to send "+ MSG1 +"; Type 'r' to send "+
                QUERY1 +"; Type 'q' to quit");
  IPC.dispatch();
  IPC.disconnect();
```

}

The file "module2.java" is the Java equivalent of module2.c.

It is a test program for IPC that publishes MSG2, and subscribes to MSG1 and QUERY. It listens for MSG1 and prints out message data. When QUERY1 is received, it publishes MSG1 and responds to the query with RESPONSE1. It exits when 'q' is typed at terminal. module2 should be run in conjunction with module1.

```
*************
import ipc.java.*;
public class module2 extends module {
 private static class msg1Handler implements IPC.HANDLER TYPE {
   msg1Handler(String theClientData) { clientData = theClientData; }
   public void handle (IPC.MSG INSTANCE msgRef, Object callData) {
     System.out.println("msg1Handler: Receiving "+
                 IPC.msgInstanceName(msgRef) +" ("+ callData
                 +") ["+ clientData +"]");
   String clientData;
 }
 private static class queryHandler implements IPC.HANDLER TYPE {
   queryHandler(String theClientData) { clientData = theClientData; }
   public void handle (IPC.MSG INSTANCE msgRef, Object callData) {
     System.out.println("queryHandler: Receiving "+
                 IPC.msgInstanceName(msgRef) +" ["+ clientData +"]");
     System.out.println(callData.toString());
     /* Publish this message -- all subscribers get it */
     String str1 = "Hello, world";
     System.out.println("\n IPC.publishData(\""+ MSG2 +"\", \""+ str1 +"\")");
     IPC.publishData(MSG2, str1);
     T2 t2 = new T2();
     t2.str1 = str1;
     /* Variable length array of one element */
     t2.t1 = new T1[1];
     t2.t1[0] = (T1) callData;
     t2.count = 1;
     t2.status = ReceiveVal;
     /* Respond with this message -- only the query handler gets it */
     System.out.println("\n IPC.respondData("+ msqRef +", \""+
                 RESPONSE1 +"\", "+ t2 +")");
     IPC.respondData(msgRef, RESPONSE1, t2);
   String clientData;
  }
 private static class stdinHnd implements IPC.FD HANDLER TYPE {
   stdinHnd(String theClientData) { clientData = theClientData; }
   public void handle (int fd) {
     try {
       int in = System.in.read();
       if (in == 'q' || in == 'Q') {
```

```
IPC.disconnect();
       System.exit(-1);
     } else {
       System.out.println("stdinHnd ["+ clientData +"]: Received "+
                      (char)in);
     // Read in any extra bytes
   while (System.in.available() > 0) System.in.read();
    } catch (Exception e) { e.printStackTrace(); }
 String clientData;
}
public static void main (String args[]) throws Exception {
  /* Connect to the central server */
  System.out.println("\nIPC.connect(\""+ MODULE2 NAME +"\")");
  IPC.connect(MODULE2 NAME);
  /* Define the messages that this module publishes */
  System.out.println("\nIPC.defineMsg(\""+ MSG2 +"\", \""+
                MSG2 FORMAT +"\")");
  IPC.defineMsg(MSG2, MSG2 FORMAT);
  System.out.println("\nIPC.defineMsg(\""+ RESPONSE1 +"\", \""+
                RESPONSE1 FORMAT +"\")");
  IPC.defineMsg(RESPONSE1, RESPONSE1 FORMAT);
  /* Subscribe to the messages that this module listens to. */
  System.out.println("\nIPC.subscribeData(\""+ MSG1 +"\", new msg1Handler(\""+
                MODULE2 NAME +"\"), int.class)");
  IPC.subscribeData(MSG1, new msg1Handler(MODULE2 NAME), int.class);
  System.out.println("\nIPC.subscribeData(\""+ QUERY1
                +"\", new queryHandler(\""+
                MODULE2 NAME +"\"), T1.class)");
  IPC.subscribeData(QUERY1, new queryHandler(MODULE2 NAME), T1.class);
  /* Subscribe a handler for tty input. Typing "q" will quit the program. */
  System.out.println("\nIPC subscribeFD(0, new stdinHnd(\""+
                MODULE1 NAME +"\"))");
  IPC.subscribeFD(0, new stdinHnd(MODULE1 NAME));
  System.out.println("\nType 'q' to quit");
  IPC.dispatch();
 IPC.disconnect();
}
```

}

File "module.java" is the Java equivalent of "module.h".

```
*****************
import IPC
WaitVal = 0
SendVal
        = 1
ReceiveVal = 2
ListenVal = 3
class T1(IPC.IPCdata) :
  _fields = ('i1', 'status', 'matrix', 'd1')
class T2(IPC.IPCdata) :
  fields = ('str1', 'count', ('t1', T1), 'status')
T1 \text{ NAME} = "T1"
# First form of "enum". 3 is the maximum value -- i.e., the value of WaitVal
T1 FORMAT = "{int, {enum : 3}, [double:2,3], double}";
T2 NAME = "T2"
# Alternate form of "enum".
T2 FORMAT = \
     "{string, int, <T1:2>, {enum WaitVal, SendVal, ReceiveVal, ListenVal}}"
MSG1
          = "message1"
MSG1_FORMAT = "int"
         = "message2"
MSG2
MSG2 FORMAT = "string"
OUERY1
            = "querv1"
QUERY1 FORMAT = T1 NAME
              = "response1"
RESPONSE1
RESPONSE1 FORMAT = T2 NAME
MODULE1 NAME = "module1"
MODULE2 NAME = "module2"
MODULE3 NAME = "module3"
______
```

File "module1.py" is the Python equivalent of "module1.c".

It publishes MSG1 and QUERY1 and subscribes to MSG2. It sends MSG1 whenever a "m" is typed at the terminal, send a QUERY1 whenever an "r" is typed, and quits the program when a "q" is typed. It should be run in conjunction with module2.

```
done = False
def stdinHnd (fd, clientData) :
 global done
  input = sys.stdin.readline()
 if (input[0] == 'q' \text{ or } input[0] == 'Q'):
    IPC.IPC disconnect()
    done = True
 elif (input[0] == 'm' or input[0] == 'M') :
    i1 = 42
   print "\n IPC publishData(%s, %d)" % (MSG1, i1)
   IPC.IPC publishData(MSG1, i1)
 elif (input[0] == 'r' or input[0] == 'R'):
   t1 = T1()
   t1.i1 = 666
    t1.status = SendVal
    t1.matrix = ((0.0, 1.0, 2.0), (1.0, 2.0, 3.0))
    t1.d1 = 3.14159
   print "\n IPC queryResponseData(%s, %s, IPC WAIT FOREVER, %s)" % \
          (QUERY1, t1, T1. name )
    (r1, ret) = IPC.IPC queryResponseData(QUERY1, t1, IPC.IPC WAIT FOREVER, T1)
   print "\n Received response"
   IPC.IPC printData(IPC.IPC msgFormatter(RESPONSE1), sys.stdout, r1)
   print "stdinHnd [%s]: Received %s" % (clientData, input),
def handlerChangeHnd (msqName, num, clientData) :
 print "HANDLER CHANGE: %s: %d" % (msgName, num)
def handlerChangeHnd2 (msgName, num, clientData) :
 print "HANDLER CHANGE2: %s: %d" % (msgName, num)
def connect1Hnd (moduleName, clientData) :
 print "CONNECT1: Connection from %s" % moduleName
                  Confirming connection (%d)" % \
        IPC.IPC isModuleConnected(moduleName)
def connect2Hnd (moduleName, clientData) :
 print "CONNECT2: Connection from %s" % moduleName
 print "
                  Number of handlers: %d" % IPC.IPC numHandlers(MSG1)
first = True
def disconnect1Hnd (moduleName, clientData) :
 global first
 print "DISCONNECT:", moduleName
 if (first) : IPC.IPC unsubscribeConnect(connect1Hnd)
 else : IPC.IPC unsubscribeConnect(connect2Hnd)
 if (first) : IPC.IPC_unsubscribeHandlerChange(MSG1, handlerChangeHnd2)
 else : IPC.IPC unsubscribeHandlerChange (MSG1, handlerChangeHnd)
 first = False
def main () :
 global done, first
 done = False; first = True
```

```
# Connect to the central server
print "\nIPC.IPC connect(%s)" % MODULE1 NAME
print IPC.IPC connect, sys.stdin, sys.stdin.fileno()
IPC.IPC connect(MODULE1 NAME)
print "HERE1"
IPC.IPC subscribeConnect(connect1Hnd, None)
IPC.IPC subscribeConnect(connect2Hnd, None)
IPC.IPC subscribeDisconnect(disconnect1Hnd, None)
# Define the named formats that the modules need
print "\nIPC.IPC defineFormat(%s, %s)" % (T1 NAME, T1 FORMAT)
IPC.IPC defineFormat(T1 NAME, T1 FORMAT)
print "\nIPC.IPC defineFormat(%s, %s)" % (T2 NAME, T2 FORMAT)
IPC.IPC defineFormat(T2 NAME, T2 FORMAT)
# Define the messages that this module publishes
print "\nIPC.IPC defineMsg(%s, IPC VARIABLE LENGTH, %s)" %(MSG1, MSG1 FORMAT)
IPC.IPC defineMsg(MSG1, IPC.IPC VARIABLE LENGTH, MSG1 FORMAT)
IPC.IPC subscribeHandlerChange (MSG1, handlerChangeHnd, None)
IPC.IPC subscribeHandlerChange (MSG1, handlerChangeHnd2, None)
print "\nIPC.IPC defineMsg(%s, IPC VARIABLE LENGTH, %s)" % \
      (QUERY1, QUERY1 FORMAT)
IPC.IPC defineMsg(QUERY1, IPC.IPC VARIABLE LENGTH, QUERY1 FORMAT)
IPC.IPC subscribeHandlerChange(QUERY1, handlerChangeHnd, None)
# Subscribe to the messages that this module listens to.
# NOTE: No need to subscribe to the RESPONSE1 message, since it is a
        response to a query, not a regular subscription!
print "\nIPC.IPC subscribeData(%s, msg2Handler, %s)" % (MSG2, MODULE1 NAME)
IPC.IPC subscribe(MSG2, msg2Handler, MODULE1 NAME)
# Subscribe a handler for tty input.
# Typing "q" will quit the program; Typing "m" will send MSG1;
# Typing "r" will send QUERY1 ("r" for response)
print "\nIPC.IPC subscribeFD(%d, stdinHnd, %s)" % \
      (sys.stdin.fileno(), MODULE1 NAME)
IPC.IPC subscribeFD(sys.stdin.fileno(), stdinHnd, MODULE1 NAME)
print "\nType 'm' to send %s; Type 'r' to send %s; Type 'q' to quit" % \
      (MSG1, QUERY1)
while (not done) : IPC.IPC listen(250)
IPC.IPC disconnect()
```

The file "module2.py" is the Python equivalent of module2.c.

It is a test program for IPC that publishes MSG2, and subscribes to MSG1 and QUERY. It listens for MSG1 and prints out message data. When QUERY1 is received, it publishes MSG1 and responds to the query with RESPONSE1. It exits when 'q' is typed at terminal. module2 should be run in conjunction with module1.

```
t2.status = ReceiveVal

# Respond with this message -- only the query handler gets it
print "\n IPC.IPC_respondData(%s, %s, %s)" % (msgRef, RESPONSE1, t2)
IPC.IPC_respondData(msgRef, RESPONSE1, t2)

done = False
```

```
global done
input = sys.stdin.readline()

if (input[0] == 'q' or input[0] == 'Q') :
    IPC.IPC_disconnect()
    done = True
else :
    print "stdinHnd [%s]: Received %s" % (clientData, input)

def main () :
    global done
    done = False
    # Connect to the central server
```

print "\nIPC.IPC connect(%s)" % MODULE2 NAME

def stdinHnd (fd, clientData) :

```
IPC.IPC connect(MODULE2 NAME)
# Define the messages that this module publishes
print "\nIPC.IPC defineMsg(%s, IPC VARIABLE LENGTH, %s)" % \
      (MSG2, MSG2 FORMAT)
IPC.IPC defineMsg(MSG2, IPC.IPC VARIABLE LENGTH, MSG2 FORMAT)
print "\nIPC.IPC_defineMsg(%s, IPC_VARIABLE_LENGTH, %s)" % \
      (RESPONSE1, RESPONSE1 FORMAT)
IPC.IPC defineMsg(RESPONSE1, IPC.IPC VARIABLE LENGTH, RESPONSE1 FORMAT)
# Subscribe to the messages that this module listens to
print "\nIPC.IPC subscribeData(%s,%s, %s)" % \
      (MSG1, msg1Handler. name , MODULE2 NAME)
IPC.IPC subscribeData(MSG1, msg1Handler, MODULE2 NAME)
print "\nIPC.IPC subscribeData(%s, %s, %s, %s)" % \
      (QUERY1 , queryHandler.__name__, MODULE2_NAME, T1.__name__)
IPC.IPC subscribeData(QUERY1, queryHandler, MODULE2 NAME, T1)
# Subscribe a handler for tty input. Typing "q" will quit the program.
print "\nIPC subscribeFD(%d, stdinHnd, %s)" % \
      (sys.stdin.fileno(), MODULE2 NAME)
IPC.IPC subscribeFD(sys.stdin.fileno(), stdinHnd, MODULE2 NAME)
print "\nType 'q' to quit"
while (not done) : IPC.IPC listen(250)
IPC.IPC disconnect()
```

Appendix B xdrgen

Purpose of xdrgen

Defining an IPC message requires a format string, which corresponds to the data structure of the message. Typically, the designer of the message has defined this format string by hand, as a macro in the same header file which defines the data structure. The xdrgen parser automates this process. It parses an XDR data structure specification (similar to a list of C type definitions) and generates a C header, which includes both type definitions and macros defining the IPC format strings.

Automating this process helps to avoid inconsistencies between the C data structure and the IPC format string. In our experience, inconsistencies are often introduced when the data structure is changed, but the person modifying the code is not aware that the format string must also be changed. These inconsistencies can lead to garbled binary messages, which are sometimes very difficult to track down.

Running xdrgen for the first time

Installing IPC will place an xdrgen binary in the same location as the central server. To see an example run of xdrgen, run the following command in the xdrgen directory of the IPC distribution:

```
> xdrgen example.xdr example.xdr.h
```

This will output example.xdr.h, a C header file based on the XDR specification in example.xdr. You can compare the two to get a quick idea of the relationship between XDR and C.

xdrgen command-line options

When xdrgen is run, it will parse xdrFile and output the resulting C header to outputHeader-File (or to stdout if outputHeaderFile isn't specified). Specifying C++ for the header output language (the default) will cause the header to use some C++ language features that are not supported by C. The differences will be discussed below.

Basic xdrgen type declarations

We now move on to the types of declarations that xdrgen can parse. There are two basic kinds of declarations. The first is a typedef. The declaration:

```
typedef int foo;
```

generates a typedef and a macro in the output header file:

```
typedef int foo;
#define foo_IPC_FORMAT "int"
```

The second kind of declaration is a struct. The declaration:

```
struct Zoo {
  int foo;
  int goo;
}
```

generates a struct and a macro in the output header file:

```
typedef struct _Zoo {
  int foo;
  int goo;
} Zoo;
#define Zoo_IPC_FORMAT "{int, int}"
```

If the header language is C++, the generated code is slightly different:

```
struct Zoo {
  int foo;
  int goo;
  #define Zoo_IPC_FORMAT "{int, int}"
  static const char *getIPCFormat(void)
      { return Zoo_IPC_FORMAT; }
};
```

If you are using a C++ compiler, the C++ output has the following advantages:

• As discussed below, xdrgen allows arbitrary code to be inserted at the end of a

struct definition. In C++, this can be used to define member functions. Defining the struct starting with "struct Zoo" instead of "typedef struct Zoo" allows one to define constructors for Zoo in the arbitrary code section.

- Code, which requires the IPC format, can access either the macro Zoo_IPC_FORMAT or the member function Zoo::getIPCFormat(), which may enable you to write cleaner code.
- You may nest struct declarations to arbitrary depths, and use previously defined types in declarations of new types, as in the following:

```
struct MyIncludableStruct {
  int foo;
  struct { int a; } goo;
};
struct MyNestedStruct {
  MyIncludableStruct b;
  struct {
    char a;
    MyIncludableStruct b2;
  } roo;
};
```

You may *not* declare multiple fields of the same type in one line, so the C construction "int a, b;" must be replaced with "int a; int b;".

Primitive types

The following struct definition has fields with all of the supported primitive types:

```
struct PrimitiveTypes {
  string a<>;
  unsigned char b;
  char c;
  unsigned int d;
  int e;
  bool f;
  float g;
  double h;
};
```

Some notes about how these types are used:

- The string field is followed by <> because strings are always variable-length arrays in XDR. This will be discussed more later.
- The bool type is not defined by default in C. Therefore, whenever xdrgen creates C-language output, it includes a definition for bool as an enumerated type compatible with the built-in C++ definition. In C++, a bool is a 4-byte data structure that takes on the values false=0 or true=1. In the IPC format string, the bool field is represented as "int".
- For the other types, there is a straightforward mapping both to C data types and to IPC format strings (see Section 3).

Fixed-length arrays

Fixed length arrays in the XDR file are mapped directly to fixed-length arrays in C. For the XDR declarations:

```
typedef unsigned char ImagePixel[3];
struct Transform {
  double mat[4][4];
};
```

we get the following header output (abbreviated for clarity):

Variable-length arrays

Variable-length arrays are specified in XDR using angle brackets <>. For the XDR declaration:

```
struct Image {
int rows;
int cols;
unsigned char data<><>;
};
```

we get the following header output (abbreviated for clarity):

```
struct Image {
  int rows;
  int cols;
  unsigned char *data;
};
#define Image_IPC_FORMAT
          "{int, int, <uchar:1,2>}"
```

Variable-length array fields in IPC must be inside a struct, and the length in each dimension of the array must correspond to an int or unsigned int field of the struct. In IPC, which fields of the struct are used for each dimension is controlled by the format string. xdrgen has the following stricter requirements:

- If the variable-length array has n dimensions, the struct must have exactly n+1 fields.
- The first n fields of the struct must have type int or unsigned int.
- The int fields of the struct correspond to dimensions of the array in order from left to right (most significant dimension to least significant).

xdrgen is designed this way to make it clear where the size of each dimension of the array is coming from, and to remove the need for extra language features to specify how int fields correspond to array dimensions. This simplicity comes at the cost of discarding some of IPC's flexibility.

Fixed and variable-length array dimensions cannot be mixed (except for strings – see below), so the following declaration is illegal:

```
struct Alpha {
  int size;
  char beta[5]<>;
}
```

However, a similar effect could be achieved with the following declaration:

```
struct Alpha {
  int size;
  struct { char data[5]; } beta<>;
};
```

For consistency with XDR, xdrgen allows a maximum possible length to be declared for a variable-length array, as in the following definition:

```
struct Gamma {
  int delta;
  float epsilon<20>;
};
```

However, there is no notion of a maximum length for a variable-length array in IPC, so the length does not currently appear in the header output.

Enumerated types

Enumerated types in XDR are mapped directly to enumerated types in C. From the declaration

```
enum Color {
   RED, ORANGE, YELLOW
};
```

we get the following header output:

```
enum Color {
   RED,
   ORANGE,
   YELLOW
};
#define Color_IPC_FORMAT
   "{enum RED,ORANGE,YELLOW}"
```

Values for the named options of an enumerated type can also be specified, but IPC is only flexible enough to handle a consecutive set of options, so if any values are specified, xdrgen represents the field as "int" to IPC (with the disadvantage that IPC cannot expand values to option names during data logging). For the declaration:

```
enum Mixed {
  TWO = 2, FOUR, SIX = 6
};
```

we get the following header output:

```
enum Mixed {
  TWO = 2,
  FOUR,
  SIX = 6
};
#define Mixed_IPC_FORMAT "int"
```

More about the string type

Strings are a special case. A string is a null-terminated array of char. IPC does not need to have an integer dimension for the size of the array because it can detect the size from the null termination. Therefore the last variable-length dimension of a string:

- is required to be present (as specified in RFC 1014),
- is ignored in the IPC format generated by xdrgen,
- does not need to appear in a struct with a corresponding int field.

Also, fixed- and variable-length arrays of strings are allowed, as in the following definition:

```
struct ExecCall {
   struct {
     int argc;
     string argv<>;
   } args;
   string envVars[20]<>;
};
```

which produces the header output (abbreviated for clarity):

Arbitrary code sections

Your XDR file can include arbitrary code sections wrapped in the delimiters % { and % }. Arbitrary code can be placed at the beginning or end of the file, between declarations, or at the end of a struct declaration, just before the closing } character. The arbitrary code will be copied into the generated header at the corresponding point in the C code.

For example, the XDR file text:

```
%{
#include "my_arbitrary_code.h"
```

```
#define N 3
extern int foo;
%}
typedef double Meters;
%{
extern Meters length;
%}
struct Roo {
  int a;
  char b;
%{
  Roo(int _a, char _b) { a=_a; b=_b; }
%}
};
```

generates the header output (abbreviated for clarity):

```
#include "my_arbitrary_code.h"
#define N 3
extern int foo;
typedef double Meters;
#define Meters_IPC_FORMAT "double"
extern Meters length;
struct Roo {
  int a;
  char b;
  Roo(int _a, char _b) { a=_a; b=_b; }
};
#define Roo_IPC_FORMAT "{int, char}"
```

External format definitions

You can use external format definitions if the structs you define using XDR contain other data types that are not defined using XDR. This could happen if you want to manually define the IPC format for a data type using an IPC feature not supported by xdrgen, or if the type definition comes from a standard system include file. For instance, the declaration:

```
ipc_type ExternalStruct1;
```

tells xdrgen to expect that the type External-Struct1 has an IPC format defined in the macro ExternalStruct1_IPC_FORMAT. The macro definition must appear before the generated code for any struct that includes ExternalStruct1, which means that it should appear either in an arbitrary code section of the XDR file or it should be included via an #include directive in an arbitrary code section.

Once ExternalStruct1 is declared using ipc_type, it can be included in subsequent struct declarations without causing a warning. For example, the declaration:

```
struct IncExternalStruct {
  int a;
  ExternalStruct1 s1;
}
```

generates the header output (abbreviated for clarity):

```
struct IncExternalStruct {
  int a;
  ExternalStruct1 s1;
}
#define IncExternalStruct_IPC_FORMAT
  "{int," ExternalStruct1 IPC FORMAT "}"
```

You can also manually define the IPC format for a type using ipc_type. Thus, the declaration:

```
ipc_type ExternalStruct2 =
    "{char, double}";
```

tells xdrgen to use the given format string instead of trying to refer to the macro External-Struct2 IPC FORMAT.

Formal XDR language definition

The xdrgen parser aims to parse the XDR language (as specified by Sun Microsystems in RFC 1014) wherever this makes sense. However, there are both unsupported features and extensions in the xdrgen input language:

 RFC 1014 specifies a mapping between an XDR data type specification and the binary format of the corresponding network message. Because XDR syntax is so similar to C syntax, there is also an implicit mapping between the XDR data type and the corresponding C data type. It is this second mapping that xdrgen tries to capture. The IPC format string for a data type is generated from the C data type according to the rules in Section 3. There is no reason to expect that IPC network messages will follow the XDR binary packing rules.

- Unsupported feature: union types. There are no corresponding types in IPC.
- Unsupported feature: hyper (8-byte integer) types. There are no corresponding types in IPC.
- Unsupported feature: optional data (the XDR * syntax). Supported in IPC, but not implemented by xdrgen.
- Extension: opaque replaced with char and unsigned char. A char type need not be in an array.
- Extension: arbitrary code sections.
- Extension: multi-dimensional arrays.

Those interested in a full grammar for the xdrgen input language can look at bison input file src/XDRGen/XDR.y in the IPC distribution.

xdrgen was developed and documented by Trey Smith, February 2001.

Index

	byte array	
\mathbf{A}	data elements	27
Access control4	data structure	27
Architecture of systems using IPC2	**	
, ,	Н	
В	Handle IPC events	16
BYTE ARRAY10	Handle IPC message	16
D11L_11d(111	Handler type	
C	connections	11
C	message	10
CHANGE HANDLE TYPE	messages with automatic unmarshalling	g 10
CHANGE_HANDLE_TYPE11	non-message events	11
Compiling IPC	subscription changes	11
Connect to IPC network	HANDLER_DATA_TYPE	
Connect to IPC Network without Listening 12	HANDLER_TYPE	
CONNECT_HANDLE_TYPE11	_	
Connecting to multiple servers	I	
Contexts	Initialize data structures	11
get31	Installing IPC	
set31	Integrate non-message & message event h	
D	integrate non-message & message event i	_
D	Interface functions	
Data formats	IPC_addOneShotTimer()	
arrays8	IPC_addPeriodicTimer()	
enumerated8	IPC addTimer()	
linked/recursive8	IPC_addTimerGetRef()	
primitives6	IPC_checkMsgFormats()	
structures	IPC connect()	
Define byte array 10	IPC_connectModule()	
Detectable errors	IPC connectModuleNoListen()	
	IPC connectNoListen()	
\mathbf{E}	IPC dataLength()	
Enable replies outside a handler	IPC defineFormat()	
Example programs	IPC_defineMsg()	
	IPC defstruct	
F	IPC defun handler()	
ED HANDLED TYPE 11	IPC_delayResponse()	
FD_HANDLER_TYPE	IPC disconnect()	
Fixed-length and variable-length arrays	IPC dispatch()	
Format strings	IPC errno	
check consistency	IPC Error	
Free	IPC ERROR TYPE	
FIEC	IPC_freeByteArray()	
	ii C_ii cob j tot ii i a y ()	4 /

IPC_freeData()	27	IPC_unmarshallData()	26
IPC_freeDataElements()	27	IPC_unsubscribe()	15
IPC_getConnections()	16	IPC_unsubscribeConnect()	18
IPC_getContext()	31	IPC_unsubscribeDisconnect()	18
IPC_handleMessage()	16	IPC_unsubscribeFD()	
IPC_initialize()	11	IPC_unsubscribeHandlerChange()	19
IPC isConnected()	12	IPC VARCONTENT PTR	10
IPC_isModuleConnected()	13	IPC_VARCONTENT_TYPE	10
IPC isMsgDefined()		IPC_VERBOSITY_TYPE	
IPC listen()	16	Is IPC network connected?	
IPC_listenClear()	16	Is message defined?	13
IPC listenWait()		Is named module connected?	
IPC marshall()			
IPC msgFormatter()		K	
IPC_msgInstanceFormatter()		killCentral()	10
IPC_msgInstanceName()		killModule()	
IPC numHandlers()		Killiviodule()	19
IPC_OK		${f L}$	
IPC parseFormat()		L	
IPC perror()		Last detected error	
IPC_printData()		Listen for given amount of time	
IPC publish()		Listen for subscribed events	16
IPC_publishData()			
IPC_publishFixed()		M	
IPC publishVC()		Marshall and publish	28
IPC_queryNotify()		Marshalling data	
IPC queryNotifyData()		Message data formats	
IPC_queryNotifyVC()		Message queue	
IPC queryResponse()		MSG INSTANCE	
IPC queryResponseData()		M26_IT.0 ITII (0E	
IPC_queryResponseVC()		N	
IPC_removeTimer()		N. 1 C 1 '1 C	1.0
IPC_removeTimerByRef()		Number of subscribers for a message	18
IPC_respond()		0	
IPC_respondData()		U	
IPC_respondVC()		Open sockets	16
IPC_RETURN_TYPE	10		
IPC_setCapacity()		P	
IPC setContext()		Pointers, linked lists, recursive data struct	ures 8
IPC_setMsgPriority()		Primitive data types	
		names and lengths	
IPC_setMsgQueueLength()		Publish	,
IPC_setVerbosity() IPC_subscribe()		fixed-length message	14
_		message	
IPC_subscribeDeta()		variable length message	
IPC_subscribeData()		randote tengin message	, 1 Т
IPC_subscribeED()		Q	
IPC_subscribeFD()		_	2.1
IPC_subscribeHandlerChange()IPC_unmarshall()		Query/response	21
IFC unmarshall()	ZD		

IPC Reference Manual

R	add	32
Register message	add by reference	
	add one shot	
Return message name	add periodic	
Return message size	remove	
Return Type	remove by reference	
S	IJ	
Select verbosity	Unmarshalling dataUnsubscribe	26
Starting the central server	file descriptor	16
Structures	me descriptor	10 1 <i>5</i>
Subscribe	messages	13
file descriptor15	new connections	
messages	new disconnections	
new connections	new subscribers to a message	19
new disconnections	V	
with automatic unmarshalling	Variable length byte array	10
	Verbosity level	11
T	·	
TIMER HANDLER TYPE32	X	
Timers	xdrgen	56