Testbed Documentation

Install DevStack

Requirements

- Ubuntu 16.04
- A single network interface with an IP address already assigned
- At least 2 cores (or more, depending on number of VMs)
- 8 GB RAM (or more, depending on number of VMs)
- 40 GB Disk

Description

- Uses an newly created user stack
- The dashboard (Horizon) can be accessed under http://<IP>/dashboard
- Login: admin or secret
- DevStack password is secret

Step 1: Prerequisites

```
Install prerequisites and create user {\tt stack}
```

```
$ sudo apt-get update
$ sudo apt-get install -y git
```

\$ sudo useradd -s /bin/bash -d /opt/stack -m stack

Switch to user stack and checkout ocata branch

```
$ sudo su - stack
```

- \$ git clone https://git.openstack.org/openstack-dev/devstack
- \$ cd devstack
- \$ git checkout stable/ocata

Step 2: Install DevStack

Adapt <code>HOST_IP</code> to match the IP address of the network interface that should be used!

\$ HOST_IP=10.0.0.110

\$ printf "[[local|localrc]]
ADMIN_PASSWORD=secret
DATABASE_PASSWORD=\\$ADMIN_PASSWORD
RABBIT_PASSWORD=\\$ADMIN_PASSWORD
SERVICE_PASSWORD=\\$ADMIN_PASSWORD
HOST_IP=\$HOST_IP

REQUIREMENTS_BRANCH=stable/ocata
HORIZON_BRANCH=stable/ocata
KEYSTONE_BRANCH=stable/ocata
NOVA_BRANCH=stable/ocata
NEUTRON_BRANCH=stable/ocata
GLANCE_BRANCH=stable/ocata
CINDER_BRANCH=stable/ocata
IRONIC_BRANCH=stable/ocata
SWIFT_BRANCH=stable/ocata

RECLONE=yes

- " | tee local.conf
- \$ # This can take 20+ minutes
- \$./stack.sh

Alternatively, to use the PROVIDER-network option where guests are spawned in the same network as the Devstack-controller (DHCP required, adapt NETWORK_GATEWAY and IPV4_ADDRS_SAFE_TO_USE accordingly):

```
$ HOST_IP=131.234.250.212
$printf "[[local|localrc]]
SERVICE_HOST=$HOST_IP
MYSQL HOST=$HOST IP
RABBIT_HOST=$HOST_IP
ADMIN PASSWORD=\$ADMIN PASSWORD
MYSQL_PASSWORD=\$ADMIN_PASSWORD
RABBIT_PASSWORD=\$ADMIN_PASSWORD
SERVICE_PASSWORD=\$ADMIN_PASSWORD
Q_ML2_PLUGIN_MECHANISM_DRIVERS=macvtap
Q_USE_PROVIDER_NETWORKING=True
enable_plugin neutron git://git.openstack.org/openstack/neutron
## MacVTap agent options
Q_AGENT=macvtap
PHYSICAL_NETWORK=default
IPV4_ADDRS_SAFE_TO_USE="203.0.113.0/24"
NETWORK_GATEWAY=203.0.113.1
PROVIDER_SUBNET_NAME="provider_net"
PROVIDER NETWORK TYPE="vlan"
SEGMENTATION_ID=2010
USE_SUBNETPOOL=False
[[post-config|/$Q_PLUGIN_CONF_FILE]]
[macvtap]
physical_interface_mappings = $PHYSICAL_NETWORK:eno1
[[post-config|$NOVA_CONF]]
force_config_drive = True
" | tee local.conf
```

Step 3: Configure guest VM connectivity

At this point DevStack is running but connectivity of guest VMs is limited (No internet access, hence no downloading of software to run on guest VMs; one cannot ssh into guest VMs). To enable internet access from guest VMs an iptables rule needs to be added.

Modify eth0 to match the interface name with the IP address configured above (HOST IP).

\$ sudo iptables -t nat -A POSTROUTING -o eth0 -j MASQUERADE

To be able to ssh into guest VMs security group rules of OpenStack need to be modified.

- \$ source devstack/accrc/admin/admin
- $\$ openstack security group rule create --proto icmp --dst-port 0 default
- \$ openstack security group rule create --proto tcp --dst-port 22 default
- \$ nova secgroup-add-rule default icmp -1 -1 0.0.0.0/0
- \$ nova secgroup-add-rule default tcp 22 22 0.0.0.0/0

Usage hints

User credentials

As user stack one has to source the admin credentials located in /opt/stack/devstack/accrc/admin/admin before being able to issue commands starting with openstack, like openstack network list (There is also a demo account that is created automatically in /opt/stack/devstack/accrc/demo/demo which has less privileges).

Example:

- \$ source /opt/stack/devstack/accrc/admin/admin
- \$ openstack project list
- \$ openstack network list

Reboot

After a reboot of the machine DevStack will not run anymore. Login as user stack an re-run

\$ /opt/stack/devstack/stack.sh

Install Kubernetes

Requirements

- Ubuntu 16.04
- A single network interface with internet connectivity
- At least 2 cores (or more, depending on number of Containers)
- 2 GB RAM (or more, depending on number of Containers)
- 20 GB Disk

Step 1: Prerequisites

```
Run as root
```

Step 2: Install Kubernetes

```
# # This can take 10+ minutes
# kubeadm init
```

To allow running kubectl as non-root user switch to that user and run:

```
$ mkdir -p $HOME/.kube
$ sudo cp -i /etc/kubernetes/admin.conf $HOME/.kube/config
$ sudo chown $(id -u):$(id -g) $HOME/.kube/config
```

Step 3: Install and configure networking

Install Pod Network Add-On Weave Net:

```
# sysctl net.bridge.bridge-nf-call-iptables=1
# kubectl apply -f "https://cloud.weave.works/k8s/net?\
k8s-version=$(kubectl version | base64 | tr -d '\n')"
```

MetalLB exposes Pods to the outside world (e.g., reachability from other VMs in the chain) by assigning an IP address to each Service with type = 'LoadBalancer'.

Install MetalLB:

```
$ kubectl apply -f https://raw.githubusercontent.com/\
google/metallb/v0.7.3/manifests/metallb.yaml
```

MetalLB needs additional information, like which pool of IP addresses to use and assign to Services. These settings are provided by applying metallb-config.yaml:

```
$ kubectl apply -f metallb-config.yaml
```

If multiple Kubernetes clusters are used then each cluster should use a different pool of IP addresses to avoid overlapping. In metallb-config.yaml adapt this part accordingly:

```
addresses:
- 10.0.0.80-10.0.0.99
```

Why MetalLB and Weave Net

MetalLB is currently the only solutions that provides support for load balancers running on bare metal clusters.

Weave Net is one of the few Kubernetes Network Add-Ons that is **supported** by MetallB . Compared to other options it provides a rich feature set.

Step 4: Allow spawning of Pods on master node

To enable spawning Pods on (this) master node:

```
$ kubectl taint nodes --all node-role.kubernetes.io/master-
```

Step 5: Using the Kubernetes Python API

The Kubernetes Python API requires specifically version 0.32.0 of the websocket-client. Python 3 additionally requires the package certifi.

That means for Python 2:

```
$ sudo pip uninstall websocket-client
$ sudo pip install -Iv websocket-client==0.32.0
That means for Python 3:
$ sudo pip3 uninstall websocket-client
$ sudo pip3 install -Iv websocket-client==0.32.0
$ pip3 install certifi
```

Add clusterrolebinding to allow the serviceaccount used by the Python API to access the API. Other options for clusterrole are clusterrole=view or clusterrole=cluster-admin

```
$ kubectl create clusterrolebinding default-edit \
    --clusterrole=edit \
    --serviceaccount=default:default \
    --namespace=default
```

An example with the minimal required code can be found in k8s-api-example.py.

The official documentation for the Python API calls provides a page for **Core** functions and **Extended** functions. These two sources provide all information needed to work with the Python API.

Step 6: Enable Docker remote API

By default the docker API can only be accessed from localhost. vimconn_kubernetes.py uses the docker API running on an Kubernetes node to request available images etc.

To allow remote access to the Docker API login as root and run:

```
# mkdir -p /etc/systemd/system/docker.service.d/
# touch /etc/systemd/system/docker.service.d/startup_options.conf
# printf "# /etc/systemd/system/docker.service.d/override.conf
[Service]
ExecStart=
ExecStart=/usr/bin/dockerd -H fd:// -H tcp://0.0.0.0:2376
" | tee /etc/systemd/system/docker.service.d/startup_options.conf
# systemctl daemon-reload
# systemctl restart docker.service
```

Install OSM

Requirements

- Ubuntu 16.04
- A single network interface with internet connectivity
- At least 4 cores
- 2 GB RAM (or more, depending on number of Containers)
- 40 GB Disk

Step 1: Install prerequisites

```
Configure LXD because OSM deploys each component (Resource Orcheststrator, Service Orcheststrator, ...) in a separate LXD container.
```

```
$ sudo apt-get update
```

- \$ sudo apt-get install -y lxd
- \$ newgrp lxd
- \$ sudo lxd init

Press ENTER until IPv6 settings pop up then select NO.

- \$ lxc list
- \$ ip address show ens3 # In case ens3 is the default interface
- \$ ip address show lxdbr0
- \$ sudo lxc profile device set default eth0 mtu 1500
- \$ exit

Step 2: Install osmclient

Install osmclient to allow subsequent invocation of commands, like osm vim-create

```
$ sudo apt-get update
```

- \$ sudo apt-get install -y software-properties-common \
 python-pip curl git
- \$ pip install python-magic
- \$ curl http://osm-download.etsi.org/repository/osm/\
 debian/ReleaseTHREE/OSM%20ETSI%20Release%20Key.gpg \
 | sudo apt-key add -
- \$ sudo add-apt-repository -y "deb [arch=amd64] \
 http://osm-download.etsi.org/repository/osm/debian/\
 ReleaseTHREE stable osmclient"
- \$ sudo apt-get update
- \$ sudo apt-get install -y python-osmclient

Step 3: Install OSM RO, SO & VCA

```
$ # This can take 20+ minutes
```

\$./install_osm.sh --lxdimages

Step 4: Configure osmclient and install vimconn-Plugins

Run

\$./install_vimconn_plugins.sh

to automatically configure environment variables needed for osmclient and install the Kubernetes vimconn-Plugin and an updated version of the OpenStack vimconn-Plugin. The difference between the old and the updated version of the OpenStack vimconn-Plugin is the connectivity of VMs. The old version

- Creates a tennant network for each network-service deployed with OSM (tennant separation
 - VMs are completely isolated from everything else than other guest
 VMs in the same tennant network
 - No connectivity to Kubernetes Pods or the internet

The new version

- Creates a tennant network for each network-service deployed with OSM (tennant separation)
- Creates a router that connects the tennant network and the public network
- Connects the router accordingly and sets it as gateway (internet access for guest VMs)




Figure 1: The new version of the OpenStack vimconn-Plugin adds a router for each tennant network. Two tennant networks (orange and green) are shown.

Install Open vSwitch-Router

Requirements

- Ubuntu 16.04
- A single network interface with internet connectivity
- One network interface per router port
- Open vSwitch $\geq 2.5.4$

Install Open vSwitch:

```
$ sudo apt-get update && \
    sudo apt-get install -y openvswitch-switch
```

Setup

- The switch acts as a router as each port is connected to a different subnet
- Each NIC is connected to one node
- All flow rules are maintained in br-core
- There is one OVS bridge connected to each NIC (e.g., eth0 is connected to br-eth0)
- Each NIC bridge (e.g., br-eth0) is connected to br-core via a patch port
- Each NIC bridge forwards all traffic from one side to the other (e.g., eth0 → br-eth0 → br-core). There is no additional forwarding/routing logic as this in br-core.

To setup this architecture login as root and modify these lines in ovs-setup.sh:

comparison of the control of th

where gatewaynic is the NIC that is used as gateway for all connected nodes and the router itself. ovs-setup.sh uses DHCP to obtain an IP address for gatewaynic.

nic and ip are arrays which contain names of NICs and corresponding IP addresses without the last dot and digit (e.g., .192.168.2.1 becomes 192.168.2) in the same order. That means ens192 belongs to 172.16.21 and so on.

subnet needs to be set to the subnet that all subnets for all ports are located in (e.g., 172.16.0.0/16 if there are router ports 172.16.21.1, 172.16.22.1, 172.16.23.1)

 ${\tt ovs-setup.sh}$ assigns IP addresses defined in ip ending in .1 for all router ports in nic.

ovs-setup.sh

- enables IPv4 forwarding in the kernel such that packet that should be forwarded will not be discarded
- install a corresponding iptables rules
- adds all OVS-bridges and OVS-patch-ports
- assigns IP addresses to each router port (except gatewaynic)

Login as root and run:

./ovs-setup.sh

Setup SDN Controller

Requirements

- Ubuntu 16.04
- A network connection which can be reached from the OVS router
- 1 core (or more, depends on traffic)
- 1 GB RAM
- 10 GB Disk

Install Ryu

```
$ sudo apt-get update
$ sudo apt-get install python-pip
$ pip install ryu
```

Start Ryu

To start the Ryu controller run

```
$ ryu-manager controller.py
```

Running Ryu blocks the terminal until it is terminated (CTRL + C). To avoid this one can use nohup, screen or tmux to run it in background.

Connect OVS router to OpenFlow Controller

To connect the OVS router to the SDN controller the controller entry needs to be set. Run as root on the OVS router

```
# controller_ip=tcp:131.234.29.73
# ovs-vsctl set-controller br-core tcp:controller_ip:6633
```

:




Figure 2: OVS Architecture

Additionally, the OVS router needs one default flow rule (priority=0) which makes it send all packets to the controller. The controller then adds all further flow rules with higher priorities. If an incoming packet does not match any of the rules added by the controller then it gets send to the controller.

```
# ovs-ofctl del-flows -00penflow13 br-core
# ovs-ofctl add-flow -00penFlow13 br-core "table=0, priority=0,\
    actions=CONTROLLER:65535"
```

Using OSM

Creating a Network Service

Descriptors can be created using an official one as a base. For each Network Service Descriptor (NSD) there needs one VNFD for each VNFD references in the NSD. That means you need at least one VNFD for each NSD. Descriptors need to be uploaded to OSM before they can be deployed. Descriptors are uploaded as zip-compressed tarball packages(_.tar.gz__). To create both descriptors it is easiest to modify the official example.

Unpack package:

```
$ tar xvf descriptor.tar.gz
```

Within each package (NSD and VNFD) there is a *.yaml*-file which is the actual descriptor.

After modifying the .yaml-file one needs to update the MD5 checksum in checksums.txt. To obtain the checksum run

```
$ md5sum cirros_vnfd.yaml
```

Create a package from a folder:

```
$ tar cvf descriptor.tar.gz descriptor
```

Before uploading a NSD to OSM one has to upload all VNFD references in the NSD. Upload a package to OSM to be able to deploy it:

```
$ osm upload-package descriptor.tar.gz
```

Before deploying a NS on OpenStack

To be able to deploy a NS on OpenStack the name of the image that is used in the VNFD must exactly match the name of an available image in OpenStack (using spaces in image names does not work). Using an image named cirros034 as in the following VNFD snippet requires a pre-upload VM image to OpenStack.

```
. . .
vdu:
   id: cirros_vnfd-VM
    name: cirros_vnfd-VM
    description: cirros_vnfd-VM
    count: 1
    # Flavour of the VM to be instantiated for the VDU
    # flavor below can fit into m1.micro
    vm-flavor:
        vcpu-count: 1
        memory-mb: 256
        storage-gb: 2
    # Image/checksum or image including the full path
    image: cirros034
Login as user stack, get/download the image, source the DevStack credentials
and run the openstack image create-command:
$ source devstack/accrc/admin/admin
$ wget http://download.cirros-cloud.net/0.3.4/cirros-0.3.4-x86_64-disk.img
$ openstack image create --file="./cirros-0.3.4-x86_64-disk.img" \
    --container-format=bare --disk-format=qcow2 cirros034
```

Adding a VIM to OSM

Use the osmclient to add a VIM to OSM. For each VIM one needs to pass the following parameters

- name Name of the VIM that is later used to deploy Network Services.
- user Username that OSM uses to access the API of the VIM
- password Password that OSM uses to access the API of the VIM
- auth_url URL that OSM uses to access the API of the VIM
- tenant Used tennant (e.g., project in OpenStack)
- config Add multiple custom options. Each VIM-connector plugin uses these options differently.
- $account_type VIM-type (e.g., openstack or kubernetes)$

Example: Add two OpenStack VIMs

```
$ osm vim-create --name openstack-1 --user admin\
    --password secret --auth_url http://131.234.29.63:5000/v2.0\
    --tenant admin --config '{public_network:\
    d84d641d-c832-4e94-bb07-ef607710e132, use_floating_ip: True}'\
```

```
--account_type openstack

$ osm vim-create --name openstack-2 --user admin\
    --password secret --auth_url http://131.234.29.65:5000/v2.0\
    --tenant admin --config '{public_network:\
    35cd1896-702e-4aba-b693-5bc27eb88e90, use_floating_ip: True}'\
    --account_type openstack
```

Example: Add two Kubernetes VIMs

Kubernetes requires a token but no user and password. Since user and password are required one can put everything there – it is not used by the VIM-connector plugin. The token cannot be placed into the password-field because it is too long. The Kubernetes VIM-connector plugin uses the config-field to reference a file that contains a token. Beside the token it also requires a ca_cert to reference the certificate file in config.

```
$ osm vim-create --name kubernetes-1 --auth_url\
    https://131.234.29.67:6443 --tenant 'default'\
    --user 'dummy' --password 'dummy'\
    --config '{"ca_cert": "/root/ca1.crt", "token":\
    "/root/token1"}' --account_type kubernetes

$ osm vim-create --name kubernetes-2 --auth_url\
    https://131.234.29.69:6443 --tenant 'default'\
    --user 'dummy' --password 'dummy'\
    --config '{"ca_cert": "/root/ca2.crt", "token":\
    "/root/token2"}' --account_type kubernetes
```

Deploying a Network Service

Testbed Specific

Credentials

On each VM

Login: userPassword: resu

\$ sudo su - stack

On DevStack there is an additional user stack. To login as stack or root first login as user and run:

```
or
$ sudo su - root
No password needed.
To enable root access without password run
$ sudo visudo
and change
%sudo ALL=(ALL:ALL) ALL
to
%sudo ALL=(ALL:ALL) NOPASSWD:ALL
```

SSH into Machines

To SSH into one of the machine, first SSH into the router. The hosts file is setup such that one can easily access all other machine by running from the router

```
$ ssh vm1
to access VM 1.
```

All machines can be accessed with the (private) SSH key from the router. That means, you can obtain easy access to the entire testbed by just putting your own (public) SSH key on the router (using ssh-copy-id).

Distribution of Function on VMs

```
• VM 1 – DevStack #1
```

- VM 2 DevStack #2
- VM 3 Kubernetes #1
- VM 4 Kubernetes #2

- VM 5 OSM
- VM 6 SDN controller
- VM 7 OVS router

VLAN Setup

$\overline{ ext{VM}}$	Network	NIC on router
vm-millian01	172.16.21.0/24	ens192
vm-millian 02	172.16.22.0/24	ens224
vm-millian 03	172.16.23.0/24	ens256
vm-millian 04	172.16.24.0/24	ens161
vm-millian 05	172.16.25.0/24	ens193
vm-millian 06	172.16.26.0/24	ens225
vm-millian08	172.16.27.0/24	ens257
${\it vm-millian} 09$	172.16.28.0/24	ens162

Routing Tables

All machines connected to the OVS router have the port connected to the router set as their gateway