

**Department of Physics,
Computer Science & Engineering**

CPSC 410 – Operating Systems I

Virtualizing Memory: Smaller Page Tables

Keith Perkins

Adapted from “CS 537 Introduction to Operating Systems”
Arpaci-Dusseau

Questions answered in this lecture:

- Review: What are problems with paging?
- Review: How large can page tables be?
- How can large page tables be avoided with different techniques?
  - multilevel page tables
- What happens on a TLB miss??

Disadvantages of Paging

1. Additional memory reference to look up in page table
   - Very inefficient
   - Page table must be stored in memory
   - MMU stores only base address of page table (processor tells it which page table to use)
   - **Avoid extra memory reference for lookup with TLBs (previous lecture)**
2. Storage for page tables may be substantial
   - Simple page table: Requires PTE for all pages in address space
     - Entry needed even if page not allocated
   - Problematic with dynamic stack and heap within address space (today)

QUIZ: How big are page Tables?

1. PTE’s are **2 bytes**, and **32** possible virtual page numbers
2. PTE’s are **2 bytes**, virtual addrs are **24 bits**, pages are **16 bytes**
3. PTE’s are **4 bytes**, virtual addrs are **32 bits**, and pages are **4 KB**
4. PTE’s are **8 bytes**, virtual addrs are **64 bits**, and pages are **4 KB**

How big is each page table?

QUIZ: How big are page Tables?

1. PTE’s are **2 bytes**, and **32** possible virtual page numbers
   32 * 2 bytes = 64 bytes
2. PTE’s are **2 bytes**, virtual addrs are **24 bits**, pages are **16 bytes**
3. PTE’s are **4 bytes**, virtual addrs are **32 bits**, and pages are **4 KB**
4. PTE’s are **8 bytes**, virtual addrs are **64 bits**, and pages are **4 KB**

How big is each page table?

QUIZ: How big are page Tables?

1. PTE’s are **2 bytes**, and **32** possible virtual page numbers
   32 * 2 bytes = 64 bytes
2. PTE’s are **2 bytes**, virtual addrs are **24 bits**, pages are **16 bytes**
   2 bytes * 2^(24 – lg 16) = 2*2^20 bytes = 2 MB
3. PTE’s are **4 bytes**, virtual addrs are **32 bits**, and pages are **4 KB**

4. PTE’s are **8 bytes**, virtual addrs are **64 bits**, and pages are **4 KB**

How big is each page table?

QUIZ: How big are page Tables?

1. PTE’s are **2 bytes**, and **32** possible virtual page numbers
   32 * 2 bytes = 64 bytes
2. PTE’s are **2 bytes**, virtual addrs are **24 bits**, pages are **16 bytes**
   2 bytes * 2^(24 – lg 16) = 2*2^20 bytes = 2 MB
3. PTE’s are **4 bytes**, virtual addrs are **32 bits**, and pages are **4 KB**
   4 bytes * 2^(32 – lg 4K) = 4*2^20 bytes = 4 MB
4. PTE’s are **8 bytes**, virtual addrs are **64 bits**, and pages are **4 KB**

How big is each page table?

QUIZ: How big are page Tables?

1. PTE's are **2 bytes**, and **32** possible virtual page numbers
   32 * 2 bytes = 64 bytes
2. PTE's are **2 bytes**, virtual addrs are **24 bits**, pages are **16 bytes**
   2 bytes * 2^(24 – lg 16) = 2*2^20 bytes = 2 MB
3. PTE's are **4 bytes**, virtual addrs are **32 bits**, and pages are **4 KB**
   4 bytes * 2^(32 – lg 4K) = 4*2^20 bytes = 4 MB
4. PTE's are **8 bytes**, virtual addrs are **64 bits**, and pages are **4 KB**
   8 bytes * 2^(64 – lg 4K) = 2^3*2^(64-12)=2^55 bytes

How big is each page table?

Why ARE Page Tables so Large?



Need 1 entry per physical frame

But you are using very few of the entries

Many invalid PT entries

Format of linear page tables:

PFN	valid	protection
10	1	r-x
-	0	-
23	1	rw-
-	0	-
-	0	-
-	0	-
-	0	-
...many more invalid...		
-	0	-
-	0	-
-	0	-
-	0	-
28	1	rw-
4	1	rw-

how to avoid storing these?

BTW where is the code?

Invalid pages are not used but still are in page table

Avoid simple linear Page Tables

Use more complex page tables, instead of just big array

Any data structure is possible with software-managed TLB

- Hardware looks for vpn in TLB on every memory access
- If TLB does not contain vpn, TLB miss
  - Trap into OS and let OS find vpn->ppn translation
  - OS notifies TLB of vpn->ppn for future accesses

Approaches

1. Multi-level Pagetables
   - Page the page tables
   - Page the page tables of page tables…

Multilevel Page Tables

Goal: Allow page tables to be allocated non-contiguously
Idea: Page the page tables

- Creates multiple levels of page tables; outer level “page directory”
- Only allocate page tables for pages in use
- Used in x86 architectures (hardware can walk known structure)



8-bit address:



Page table has 12 rows not 16

Virtual address Physical address
0x01 in P0 offset 1 0x11
0x43 => 0100 0011 =>invalid
0xF5 => 1111 0101 => 0x25

Quiz: Multilevel

page directory		page of PT (@PPN:0x3)		page of PT (@PPN:0x92)		
PPN	valid	PPN	valid	PPN	valid	
0x3	1	0x10	1	-	0	
-	0	0x23	1	-	0	
-	0	-	0	-	0	
-	0	-	0	-	0	translate 0x01ABC
-	0	0x80	1	-	0	
-	0	0x59	1	-	0	
-	0	-	0	-	0	translate 0x00000
-	0	-	0	-	0	
-	0	-	0	-	0	
-	0	-	0	-	0	
-	0	-	0	-	0	
-	0	-	0	-	0	translate 0xFEED0
-	0	-	0	-	0	
-	0	-	0	-	0	
-	0	-	0	-	0	
	0	-	0	0x55	1	
0x92	1	-	0	0x45	1	

20-bit address:

Quiz: Multilevel

page directory		page of PT (@PPN:0x3)		page of PT (@PPN:0x92)	
PPN	valid	PPN	valid	PPN	valid
0x3	1	0x10	1	-	0
-	0	0x23	1	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	0x80	1	-	0
-	0	0x59	1	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
	0	-	0	0x55	1
0x92	1	-	0	0x45	1

translate 0x01ABC

0x23ABC

translate 0x00000

translate 0xFEED0

20-bit address:

Quiz: Multilevel

page directory		page of PT (@PPN:0x3)		page of PT (@PPN:0x92)	
PPN	valid	PPN	valid	PPN	valid
0x3	1	0x10	1	-	0
-	0	0x23	1	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	0x80	1	-	0
-	0	0x59	1	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
	0	-	0	0x55	1
0x92	1	-	0	0x45	1

translate 0x01ABC

0x23ABC

translate 0x00000

0x10000

translate 0xFEED0

20-bit address:

Quiz: Multilevel

page directory		page of PT (@PPN:0x3)		page of PT (@PPN:0x92)	
PPN	valid	PPN	valid	PPN	valid
0x3	1	0x10	1	-	0
-	0	0x23	1	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	0x80	1	-	0
-	0	0x59	1	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
-	0	-	0	-	0
	0	-	0	0x55	1
0x92	1	-	0	0x45	1

translate 0x01ABC

0x23ABC

translate 0x00000

0x10000

translate 0xFEED0

0x55ED0

20-bit address:

QUIZ: Address format for multilevel Paging

30-bit address:

How should logical address be structured?

- How many bits for each paging level?

Goal?

- Each page table fits within a page
- PTE size * number PTE = page size
  - Assume PTE size = 4 bytes
  - Page size = 2^12 bytes = 4KB ← Want entire page table to fit in
  - 2^2 bytes * number PTE = 2^12 bytes ← can have 1024 4byte rows
  - number PTE = 2^10
- # bits for selecting inner page = 10

Remaining bits for outer page:

- 30 – 10 – 12 = 8 bits

Problem with 2 levels?

Problem: page directories (outer level) may not fit in a page

64-bit address:

Solution:

- Split page directories into pieces
- Use another page dir to refer to the page dir pieces.



How large is virtual address space with 4 KB pages, 4 byte PTEs, each page table fits in page given 1, 2, 3 levels? Assume 10 bits/level (1K)

4KB / 4 bytes -- 1K entries per level

1 level: 1K * 4K = **2^22** = 4 MB

2 levels: 1K * 1K * 4K = **2^32** ≈ 4 GB

3 levels: 1K * 1K * 1K * 4K = **2^42** ≈ 4 TB

QUIZ: FULL SYSTEM WITH TLBS

On TLB miss: lookups with more levels more expensive

How much does a miss cost?

Assume 3-level page table

Assume 256-byte pages (8 bits)

Assume 16-bit addresses (so 8 bits for 3 levels)

ASID	VPN	PFN	Valid
211	0xbb	0x91	1
211	0xff	0x23	1
122	0x05	0x91	1
211	0x05	0x12	0

Assume ASID of current process is 211

How many physical accesses for each instruction? (Ignore previous ops changing TLB

a) 0xAA10: movl 0x1111, %edi

0xaa: (TLB miss -- 3 for addr trans) + 1 instr fetch

0x11: (TLB miss -- 3 for addr trans) + 1 movl

Total: 8

(b) 0xBB13: addl $0x3, %edi

(c) 0x0519: movl %edi, 0xFF10

0xbb: (TLB hit -- 0 for addr trans) + 1 instr fetch from 0x9113

Total: 1

0x05: (TLB miss -- 3 for addr trans) + 1 instr fetch

0xff: (TLB hit -- 0 for addr trans) + 1 movl into 0x2310

Total: 5

Summary:
Better PAGE TABLES

Problem:
Simple linear page tables require too much contiguous memory
If Hardware handles TLB miss, page tables must follow specific format

- Multi-level page tables used in x86 architecture
- Each page table fits within a page