ossec-authd

The ossec-authd program will automatically add an agent to a Wazuh manager and provide the key to the agent. The agent-auth application is the client application used with ossec-authd creates an agent with an ip address of "any" instead of using its actual IP.

A Warning

By default there is no authentication or authorization involved in this transaction, so it is recommended that this daemon only be run when a new agent is being added.

-V	Version and license message.				
-h	This help message.				
-d	Debug mode. Use this parameter multiple times to increase the debug level.				
-t	Test configuration.				
-f	Run in foreground.				
-i	Use client's source IP address instead of any.				
-F <time></time>	Remove old agent with same name or IP if its keepalive has more than <time> seconds.</time>				
-F no	Disable force insertion.				
-r	Do not keep removed agents (delete).				
-g <group></group>	Group to run as.				
	Default	ossec			
	Directory to chroot into.				
-D <dir></dir>	Default	/var/ossec			
	Manager port.				
-p <port></port>	Default	1515			
-P	Enable shared password authentication, at /var/ossec/etc/authd.pass or random.				
-v <path></path>	Full path to CA certificate used to verify clients.				
-s	Used with -v, enable source host verification.				
-x <path></path>	Full path to server certificate.				
	Default	/var/ossec/etc/sslmanager.cert.			
-k <path></path>	Full path to server key.				
	Default	/var/ossec/etc/sslmanager.key.			
-a	Auto negotiate the most secure common SSL/TLS method with the client.				
	Default	TLS v1.2 only (if supported by the server).			