

## Update existing CRC 1.1 Hot Masternode to 1.2 on Linux Manually

- 1. Go to the directory containing the crowncoin-cli stop your Masternode by running the following command:
- ./crowdcoin-cli stop
- 2. Backup (make a copy of) your wallet.dat present in your ~/.crowdcoincore folder in a secure place (do not move it)
- 3. Download binaries files by downloading them from github

```
git clone
```

https://github.com/crowdcoinChain/Crowdcoin/releases/download/1.2.0/Crowdcoin\_command\_line\_binaries\_linux\_1.2.tar.gz

And replace the current binaries, or just decompress with this command

tar -zxvf Crowdcoin\_command\_line\_binaries\_linux\_1.2.tar.gz
cd Crowdcoin\_command\_line\_binaries\_linux\_1.2

- 4. start your Crowdcoin daemon by running the following command
- ./crowdcoind -d

Running the following command to confir it's started

./crowdcoin-cli getinfo

you should see the version has been update from

"version": 120106 for the old version

to

"version": 130101 for the new version

- 5. wait for sync, you can check with
- ./crowdcoin getinfo

So that last block match the one on <a href="https://explorer.crowdcoin.site">https://explorer.crowdcoin.site</a>

- 6. As collateral has change for CRC Masternode, you need to to get 1500 CRC, check your current balance with the following command :
- ./crowdcoin-cli getbalance

If you don't have enough fund (1500CRC), you have to send more CRC

To get the address to send the fund to, type

./crowdcoin-cli getaccountaddress 0

This will display the address. Send at least to have 1501 on this address "wallet\_address" to cover fees used in step 7

## Run

./crowdcoin-cli getbalance

Until you see the 1501 CRC



7. Now we will create a new address for your masternode and send the 1500CRC Collateral type: ./crowdcoin-cli getnewaddress MN1500 Please notethis address, we call it "MN1500\_address" below This will display the new address of the masternode where you have to send the 1500 CRC To send 1500CRC from you masternode (if you have enough fund on it, see step 7), type ./crowdcoin-cli sendtoaddress "MN1500\_address" 1500 8. Now we have to wait to get a new transaction Id, you can check by typing ./crowdcoin-cli masternode outputs if no transaction appear like this } Check the CRC <a href="https://explorer.crowdcoin.site">https://explorer.crowdcoin.site</a> to see what happen to your transaction. when the transaction is validated and confirmed you should see this: xxxxxxxxx-yy Please note this "transaction-id" for step 12 9. Generate new masternode genkey by typing the following command ./crowdcoin-cli masternode genkey Please note "genkey" for step 11 10. Stop again your masternode by typing ./crowdcoin-cli stop 11. Modify the crowdcoin.conf located in ~/.crowdcoincore modify the line masternodeprivkey="genkey" "genkey" is the output in step 9 without the quote, then save and close the file 12. Modify the masternode.conf located in ~/.crowdcoincore Add the line without the quote (") mn1500 127.0.0.1:12875 "genkey" "transaction-id" Save and close the file 13. Restart your masternode by running the following command: ./crowdcoind -d 14. Start your masternode by running the followinf command ./crowdcoin-cli masternode start 15.check you masternode node by running the following command ./crowdcoin-cli masternode status

16. To debug run

tail -f ~/.crowdcoincore/debug.log