

HSMoD Service

HYPERLEDGER FABRIC (BLOCKCHAIN) INTEGRATION GUIDE



Document Information

Product Version	1.7
Document Part Number	007-013897-001
Release Date	21 November 2018

Revision History

Revision	Date	Reason	
Rev. A	17 August 2017	For initial release 1.1.0	
Rev. B	19 September 2017	For release 1.1.1	
Rev. C	14 November 2017	For release 1.2	
Rev. D	05 February 2018	For release 1.3	
Rev. E	02 March 2018	For HSM on Demand release 1.3	
Rev. F	05 April 2018	April 2018 For release 1.4	
Rev. G	07 May 2018 For HSM on Demand release 1.4		
Rev. H	10 June 2018	For release 1.5	
	12 September 2018	For release 1.6	
	21 November 2018	For release 1.7	

Trademarks and Copyrights

Copyright 2018 Gemalto. All rights reserved. Gemalto and the Gemalto logo are trademarks and service marks of Gemalto and/or its subsidiaries and are registered in certain countries. All other trademarks and service marks, whether registered or not in specific countries, are the property of their respective owners.

Disclaimer

All information herein is either public information or is the property of and owned solely by Gemalto and/or its subsidiaries who shall have and keep the sole right to file patent applications or any other kind of intellectual property protection in connection with such information.

Nothing herein shall be construed as implying or granting to you any rights, by license, grant or otherwise, under any intellectual and/or industrial property rights of or concerning any of Gemalto's information.

This document can be used for informational, non-commercial, internal, and personal use only provided that:

- > The copyright notice, the confidentiality and proprietary legend and this full warning notice appear in all copies.
- > This document shall not be posted on any publicly accessible network computer or broadcast in any media, and no modification of any part of this document shall be made.

Use for any other purpose is expressly prohibited and may result in severe civil and criminal liabilities.

The information contained in this document is provided "AS IS" without any warranty of any kind. Unless otherwise expressly agreed in writing, Gemalto makes no warranty as to the value or accuracy of information contained herein.

The document could include technical inaccuracies or typographical errors. Changes are periodically added to the information herein. Furthermore, Gemalto reserves the right to make any change or improvement in the specifications data, information, and the like described herein, at any time.

Gemalto hereby disclaims all warranties and conditions with regard to the information contained herein, including all implied warranties of merchantability, fitness for a particular purpose, title and non-infringement. In no event shall Gemalto be liable, whether in contract, tort or otherwise, for any indirect, special or consequential damages or any damages whatsoever including but not limited to damages resulting from loss of use, data, profits, revenues, or customers, arising out of or in connection with the use or performance of information contained in this document.

Gemalto does not and shall not warrant that this product will be resistant to all possible attacks and shall not incur, and disclaims, any liability in this respect. Even if each product is compliant with current security standards in force on the date of their design, security mechanisms' resistance necessarily evolves according to the state of the art in security and notably under the emergence of new attacks. Under no circumstances, shall Gemalto be held liable for any third party actions and in particular in case of any successful attack against systems or equipment incorporating Gemalto products. Gemalto disclaims any liability with respect to security for direct, indirect, incidental or consequential damages that result from any use of its products. It is further stressed that independent testing and verification by the person using the product is particularly encouraged, especially in any application in which defective, incorrect or insecure functioning could result in damage to persons or property, denial of service, or loss of privacy.

All intellectual property is protected by copyright. All trademarks and product names used or referred to are the copyright of their respective owners. No part of this document may be reproduced, stored in a retrieval system or transmitted in any form or by any means, electronic, mechanical, chemical, photocopy, recording or otherwise without the prior written permission of Gemalto.

SafeNet Data Protection on Demand 1.7

HYPERLEDGER FABRIC (BLOCKCHAIN) INTEGRATION GUIDE

Contents Third Party Application Details ______5 Supported Platforms 5 Constraints on HSMoD Services 6 Install Unix Components 7 Set up Docker ______ 7 Configuring HyperLedger Fabric to use PKCS11 Blockchain Cryptographic Service Provider (BCCSP) ... 9 Generating a Certificate Signing Request using fabric-ca-client and PKCS11 BCCSP ______10 Configuring the Peer nodes11 Generating a CSR _______13 Example Configuration: Running e2e cli end-2-end execution ________13

Overview

This guide demonstrates using an HSM on Demand Service's PKCS#11 API to securely store a Hyperledger Admin Certificate Authority (CA), Peer, and Orderer private keys. The guide then provides examples of the e2e cli end-to-end execution for creating channels and querying the chaincode.

This integration guide features sample material to demonstrate the process of integrating your HSM on Demand Service with Blockchain HyperLedger Fabric.

Using an HSM on Demand Service to generate the ECDSA signing keys for Blockchain Identities provides the following benefits:

- > Secure generation, storage, and protection of Identity signing keys on a FIPS 140-2 level 3 validated HSM*.
- > Full life cycle management of the keys.
- > Performance improvements resulting from off-loading cryptographic operations from application servers to the HSM on Demand Service.

This document contains the following sections:

- Preparing for the Integration on page 6
- "Integrating Hyperledger Fabric (Blockchain) with an HSM on Demand Service" on page 9

Third Party Application Details

This integration guide uses the following third party applications:

- > Hyperledger Fabric
- > Hyperledger Fabric CA

Supported Platforms

The following platforms are tested with HSMoD Service:

Platforms Tested	Golang	Docker	Docker Compose
RHEL 64-bit	1.8.3	17.06.0-ce	1.8.0

^{*}Validation in progress

Preparing for the Integration

Before you proceed with the integration, ensure you have completed the following:

- > "Provision HSM on Demand Services" below
- > "Install Unix Components" on the next page
- > "Set up Golang" on the next page
- > "Set up Docker" on the next page

Provision HSM on Demand Services

Follow the instructions in the *HSM* on *Demand Application Owner Quick Start Guide* and complete the following:

- 1. Select the Hyperledger tile and create the following three HSM on Demand Services.
 - org1.example.com
 - org2.example.com
 - orderer.example.com
- 2. For each service create a client with the same name, and download the zip to the host machine.
- 3. Execute the following commands to create the service directories on the host machine.
 - # mkdir -p /etc/hyperledger/fabric/dpod/org1.example.com
 - # mkdir -p /etc/hyperledger/fabric/dpod/org2.example.com
 - # mkdir -p /etc/hyperledger/fabric/dpod/orderer.example.com
- **4.** Unzip the three clients in their respective directories.
- 5. Initialize the service, Crypto Officer, and Crypto User roles on the services. For the purpose of this integration guide, the passwords have been set to userpin. Follow the instructions in the Application Owner Quick Start Guide and set the ChrystokiConfigurationPath environment variable to point to the Chrystoki.conf file.



NOTE In a production configuration the passwords should be set to coincide with your organization's security policy.



NOTE We recommend using separate HSMoD Service's for the Peer, Orderer, and Users roles.

Constraints on HSMoD Services

Please take the following limitations into consideration when integrating your application software with an HSM on Demand Service.

HSM on Demand Service in FIPS mode

HSMoD services operate in a FIPS and non-FIPS mode. If your organization requires non-FIPS algorithms for your operations, ensure you enable the **Allow non-FIPS approved algorithms** check box when configuring your HSM on Demand service. The FIPS mode is enabled by default.

Refer to the *Mechanism List* in the SDK Reference Guide for more information about available FIPS and non-FIPS algorithms.

Verify HSM on Demand <slot> value

LunaCM commands work on the current slot. If there is only one slot, then it is always the current slot. If you are completing an integration using HSMoD services, you need to verify which slot on the HSMoD service you send commands to. If there is more than one slot, then use the **slot set** command to direct a command to a specified slot. You can use **slot list** to determine which slot numbers are in use by which HSMoD service.

Install Unix Components

The following components must be installed on the host system where you will generate the keys for the User, Peer, and Orderer:

- > Git
- > Curl
- > Alien
- > Python

Execute the following command as a user with privileges to install the components:

sudo apt-get install git curl alien python-pip libtool libltdl-dev

Set up Golang

Hyperledger Frabric uses the Go programming language. Download the golang binaries from https://golang.org/dl/. Follow the instructions at https://golang.org/doc/install and install the golang binaries. Ensure that the GO program is in the PATH variable.

export PATH=/usr/local/go/bin:\$PATH

If the GOPATH is not set, set it. The value will be a directory of the development workspace.

export GOPATH=/opt/gopath

mkdir -p \$GOPATH/src/github.com/hyperledger

cd \$GOPATH/src/github.com/hyperledger

Set up Docker

Docker and Docker-compose need to be installed on the host system. Follow the instructions at https://docs.docker.com/engine/installation/linux/docker-ce/ubuntu/ to install the Docker-CE.

Execute **sudo pip install docker-compose==1.8.0** to install the docker-compose.

You can configure Docker so that it does not require **sudo**. Execute:

sudo gpasswd -a \$USER docker

newgrp docker

Update the Dockerfiles

You need to add a command to the peer and orderer **Dockerfile.in** to install the libtool.

To update the Dockerfiles

1. Open the images/orderer/Dockerfile.in in a text editor.

Add

```
RUN apt-get update && apt-get install -y libtool
```

After

```
RUN mkdir -p /var/hyperledger/production $FABRIC_CFG_PATH
```

2. Open the images/peer/Dockerfile.in in a text editor.

Add

```
RUN apt-get update && apt-get install -y libtool
```

After

RUN mkdir -p /var/hyperledger/production \$FABRIC CFG PATH

Integrating Hyperledger Fabric (Blockchain) with an HSM on Demand Service

This guide will detail how to generate keys for the User, Peer, and Orderer roles on the HSM on Demand Servicein an example configuration. It will then demonstrate the e2e_cli end-to-end execution for creating channels and querying the chaincode.

This integration contains the following topics:

- "Configuring HyperLedger Fabric to use PKCS11 Blockchain Cryptographic Service Provider (BCCSP)" below
- > "Generating a Certificate Signing Request using fabric-ca-client and PKCS11 BCCSP" on the next page
- > "Integrating Hyperledger Fabric (Blockchain) with an HSM on Demand Service" above
- > "Integrating Hyperledger Fabric (Blockchain) with an HSM on Demand Service" above
- > "Integrating Hyperledger Fabric (Blockchain) with an HSM on Demand Service" above
- > "Example Configuration: Running e2e_cli end-2-end execution" on page 13

Configuring HyperLedger Fabric to use PKCS11 Blockchain Cryptographic Service Provider (BCCSP)

You must make modifications to the Hyperledger Fabric configuration files before you can begin generating keys using the PKCS11 Blockchain Cryptographic Service Provider (BCCSP).

To configure HyperLedger Fabric to use PKCS11 BCCSP

1. Create the Hyperledger fabric repository:

git clone https://gerrit.hyperledger.org/r/fabric

cd fabric

 Open the docker-env.mk file in a text editor. Remove the -static linking option from the DOCKER_GO_ LDFLAGS line.

Original: DOCKER_GO_LDFLAGS += -linkmode external -extldflags '-static -lpthread'

Updated: DOCKER GO LDFLAGS += -linkmode external -extldflags '-lpthread'

3. Compile the docker images and executables

```
# make docker
# make release
```

4. Clone the fabric-ca project and build the fabric-ca client binary.

```
# cd $GOPATH/src/github.com/hyperledger
# git clone https://gerrit.hyperledger.org/r/fabric-ca
# cd fabric-ca
# git checkout -b v1.1.0 v1.1.0
```



NOTE This integration guide was developed using the v1.1.0 tag. We recommend you use this version, as the instructions may not be compatible with the latest versions available in the master branch of Hyperledger Fabric project.

make fabric-ca-client

Generating a Certificate Signing Request using fabric-ca-client and PKCS11 BCCSP

The fabric-ca-client utility can be used to generate certificate signing requests (CSR) for Peers, Orderers, and Users in their respective MSP directories.

The fabric-ca-client utility uses the BCCSP to generate cryptographic material. If you configure the BCCSP to use a PKCS11 implementation, you can generate and store the keys using the HSM on Demand Service.

You must update the fabric-ca-client-config.yaml to use the PKCS11 cryptographic provider, configure the Orderer and Peer nodes, and initialize communication between the objects.

Configuring the User nodes

You must configure the User nodes by updating the **fabric-ca-client-config.yaml** file to use the PKCS11 cryptographic provider.

You can do this by updating the file in a text editor or exporting the environment variables. See:

- > "To update the fabric-ca-client-config.yaml in a text editor" below
- > "To update the fabric-ca-client-config.yaml using environment variables" on the next page

To update the fabric-ca-client-config.yaml in a text editor

1. Open the ~/.fabric-ca-client/fabric-ca-client-config.yaml file in a text editor and update the file for your configuration. The following is an example of a BCCSP configuration using an HSM on Demand Service.

```
default: PKCS11
sw:
    hash: SHA2
    security: 256
    filekeystore:
        # The directory used for the software file-based keystore
        keystore: msp/keystore
pkcs11:
    library: /etc/hyperledger/fabric/dpod/org1.example.com/libs/64/libCryptoki2.so
    pin: userpin
    label:
    hash: SHA2
    security: 256
    filekeystore:
        # The directory used for the software file-based keystore
        keystore: msp/keystore
```

2. Add a **keyrequest** setting to the **csr** section to specify the key size.

```
Add: KeyRequest:
```

A: ecdsa S: 256

To update the fabric-ca-client-config.yaml using environment variables

1. Export the following environment variables to configure the **fabric-ca-client-config.yaml** file. Execute the following to export the values:

```
# export FABRIC_CA_CLIENT_BCCSP_DEFAULT=PKCS11
# export FABRIC_CA_CLIENT_BCCSP_PKCS11_LABEL=<HSMoD_service_label>
# export FABRIC_CA_CLIENT_BCCSP_PKCS11_PIN=<HSMoD_SO_password>
# export FABRIC_CA_CLIENT_BCCSP_PKCS11_LIBRARY=<PKCS11_library>
```

Configuring the Peer nodes

To configure the Peer nodes to access the HSM on Demand Service keys you must update the **core.yaml** file or set the environment variables for the following:

- > PKCS11 BCCSP cryptographic library
- > the HSM on Demand Service
- > HSM on emand Servicepassword
- > location of the configuration files

You can do this by updating the file in a text editor or exporting the environment variables. See:

- > "To update the core.yaml file in a text editor" below
- "To update the core.yaml file using environment variables" below

Additionally, you must mount the **core.yaml** file in the volumes section . The **core.yaml** file provides basic configuration options for Peer modules.

To update the core.yaml file in a text editor

- 1. Open the **core.yaml** file in a text editor.
- Specify PKCS11 as the default cryptographic provider in the BCCSP section. The file should appear as follows:

```
BCCSP:
Default: PKCS11
PKCS11:
# TODO: The default Hash and Security level needs refactoring to be
# fully configurable. Changing these defaults requires coordination
# SHA2 is hardcoded in several places, not only BCCSP
Hash: SHA2
Security: 384
Library: /etc/hyperledger/fabric/dpod/org1.example.com/libs/64/libCryptoki2.so
Label: <organization_label>
Pin: <password>
SoftwareVerify: true
SensitiveKeys: true
#FileKeyStore:
# KeyStore:
```

To update the core.yaml file using environment variables

1. Export the following environment variables to change the configuration settings of the core.yaml file.

```
# export CORE_PEER_BCCSP_DEFAULT=PKCS11
# export CORE_PEER_BCCSP_PKCS11_LABEL=<HSMoD_service_label>
# export CORE_PEER_BCCSP_PKCS11_PIN=<HSMoD_SO_password>
# export CORE_PEER_BCCSP_PKCS11_LIBRARY=<PKCS11_library>
```

2. Ensure that the HSM on Demand Service client directory is available to the peer, and is using the correct HSM on Demand Service for the peer. The **ChrystokiConfigurationPath** must point to the HSM on Demand Service client directory, where the **Crystoki.conf** is stored.

```
# export ChrystokiConfigurationPath=<path_to_Chrystoki.conf>
```

Configuring the Orderer nodes

To configure the Orderer nodes to access the HSM on Demand Service keys you must update the **orderer.yaml** file or set the environment variables for the following:

- > PKCS11 BCCSP cryptographic library
- > the HSM on Demand Service
- > HSM on Demand Service password
- > location of the configuration files

You can do this by updating the file in a text editor or exporting the environment variables. See:

- > "To update the orderer.yaml file in a text editor" below
- > "To update the orderer.yaml file using environment variables" below

Additionally, you must mount the **orderer.yaml** file in the volume section. The **orderer.yaml** file provides basic configuration options for Orderer modules.

To update the orderer yaml file in a text editor

- 1. Open the **orderer.yaml** file in a text editor.
- 2. Specify PKCS11 as the default cryptographic provider in the BCCSP section. The file should appear as follows:

```
BCCSP:
Default: PKCS11
PKCS11:
# TODO: The default Hash and Security level needs refactoring to be
# fully configurable. Changing these defaults requires coordination
# SHA2 is hardcoded in several places, not only BCCSP
Hash: SHA2
Security: 384
Library: /etc/hyperledger/fabric/dpod/orderer.example.com/libs/64/libCryptoki2.so
Label: <organization_label>
Pin: <password>
SoftwareVerify: true
SensitiveKeys: true
#FileKeyStore:
# KeyStore:
```

To update the orderer.yaml file using environment variables

1. Export the following environment variables to change the configuration settings of the **orderer.yaml** file.

```
# export ORDERER_GENERAL_BCCSP_PKCS11_LABEL=<HSMoD_service_label>
# export ORDERER GENERAL BCCSP_PKCS11_PIN=<HSMoD_SO_password>
```

- # export ORDERER GENERAL BCCSP PKCS11 LIBRARY=<PKCS11 library>
- 2. Ensure that the HSM on Demand Service client directory is available to the peer, and is using the correct HSM on Demand Service for the peer. The **ChrystokiConfigurationPath** must point to the HSM on Demand Service client directory, where the **Crystoki.conf** is stored.
 - # export ChrystokiConfigurationPath=<path to Chrystoki.conf>

Generating a CSR

You must generate a CSR for each role node in the configuration. You need to adjust the options and variables for the requirements of the particular CSR.

The command to generate a CSR utilizes the following syntax:

./fabric-ca-client gencsr --csr.cn <value> --mspdir <value> --csr.names <value>

Argument	Description
csr.cn <value></value>	The common name field of the certificate signing request.
mspdir <value></value>	Path to the Membership Service Provider directory.
csr.names <value></value>	A list of comma-separated CSR labels of the form <name>=<value>. Values include: C=<country>, ST=<state>, OU=<user_role></user_role></state></country></value></name>



NOTE When generating CSR requests ensure that you specify the correct CN, MSP directory, and CSR names. The OU value should equate to peer, orderer or client, depending on the CSR.

To generate the User CSR

1. Execute the following to generate the User CSR for **org1.example.com**.

```
# ./fabric-ca-client gencsr --csr.cn <common_name_for_CSR> --mspdir <MSP_directory> --csr.names
"C=US,ST=California,L=San Francisco,OU=<OU>"
```

2. Submit the CSR to your CA to obtain the signed certificate for the role, and place the signed certificate in the respective **msp/signcerts** directory.

Example Configuration: Running e2e_cli end-2-end execution

The following procedural set provides an example e2e_cli end-2-end execution configuration. Before beginning this procedural set, it is assumed you have completed the prerequisite sections of the documentation set, and the preceding tasks.

- 1. Copy the compiled **fabric-ca-client** to the **examples/e2e_cli** directory.
 - # cd \$GOPATH/src/github.com/hyperledger/fabric-ca/
 - # cp bin/fabric-ca-client ../fabric/examples/e2e cli
- 2. Copy the following script and save the file as **gencerts.sh**.



NOTE The script works in conjunction with the **cryptogen** tool. The script generates all of the Peer, Orderer, and Admin user MSPs using the **fabric-ca-client gencsr** command. Certificate are generated using **openssl**.

#!/bin/bash #Copyright (C) 2017 SafeNet. All rights reserved. # This script generates certificates and keys to work with the cryptogen util # to be used with the e2e cli hyperledger fabric example. # This allows the keys for the certificate to be generated with the # PKCS11 BCCSP which in turn allows keys to be generated in an HSM. CA CLIENT=./fabric-ca-client CRYPTO CONFIG=\$PWD/crypto-config ROOT=\$PWD BCCSP DEFAULT=PKCS11 PIN=userpin check error() { if [\$? -ne 0]; then echo "ERROR: Something went wrong!" exit 1 fi } signcsr() { MSP=\$1 CN=\$2 CA DIR=\$3 CA NAME=\$4 CA CERT=\$(find \$CA DIR -name "*.pem") CA KEY=\$(find \$CA DIR -name "* sk") CSR=\$MSP/signcerts/\$CN.csr CERT=\$MSP/signcerts/\$CN-cert.pem openssl x509 -req -sha256 -days 3650 -in \$CSR -CA \$CA CERT -CAkey \$CA KEY -CAcreateserial -out SCERT check error genmsp() { ORG DIR=\$1 ORG NAME=\$2 NODE DIR=\$3 NODE NAME=\$4 NODE OU=\$6 CN=\${NODE NAME}\${ORG NAME} CA PATH=\$CRYPTO CONFIG/\$ORG DIR/\$ORG NAME NODE PATH=\$CA PATH/\$NODE DIR/\$CN MSP=\$NODE PATH/msp TLS=\$NODE PATH/tls

LABEL=\$5

```
rm -rf $MSP/keystore/*
  rm -rf $MSP/signcerts/*
  echo $LABEL
  export FABRIC CA CLIENT BCCSP DEFAULT=$BCCSP DEFAULT
  export FABRIC CA CLIENT BCCSP PKCS11 LABEL=$LABEL
  export FABRIC_CA_CLIENT_BCCSP_PKCS11_PIN=$PIN
  export ChrystokiConfigurationPath=/etc/hyperledger/fabric/dpod/$LABEL
  export FABRIC_CA_CLIENT_BCCSP_PKCS11_
LIBRARY=/etc/hyperledger/fabric/dpod/$LABEL/libs/64/libCryptoki2.so
  $CA CLIENT gencsr --csr.cn $CN --mspdir $MSP --csr.names "C=US,ST=California,L=San
Francisco, OU=$NODE OU"
  check_error
  signcsr $MSP $CN $CA PATH/ca $ORG NAME
copy admin cert node() {
  ORG DIR=$1
  ORG NAME=$2
 NODE DIR=$3
 NODE NAME=$4
  CN=$NODE NAME.$ORG NAME
  CA PATH=$CRYPTO CONFIG/$ORG DIR/$ORG NAME
  NODE PATH=$CA PATH/$NODE DIR/$CN
  MSP=$NODE PATH/msp
  ADMIN CN=Admin@$ORG NAME
  ADMIN CERT=$CA PATH/users/$ADMIN CN/msp/signcerts/$ADMIN CN-cert.pem
  cp $ADMIN CERT $NODE PATH/msp/admincerts
  check error
copy admin cert ca() {
 ORG DIR=$1
  ORG NAME=$2
  CA PATH=$CRYPTO CONFIG/$ORG DIR/$ORG NAME
  ADMIN CN=Admin@$ORG NAME
  ADMIN CERT=$CA PATH/users/$ADMIN CN/msp/signcerts/$ADMIN CN-cert.pem
  cp $ADMIN CERT $CA PATH/msp/admincerts
  check error
  cp $ADMIN CERT $CA PATH/users/$ADMIN CN/msp/admincerts
  check error
for org in 1 2; do
  for peer in 0 1; do
   genmsp peerOrganizations org${org}.example.com peers peer${peer}. org${org}.example.com
peer
  genmsp peerOrganizations org${org}.example.com users Admin@ org${org}.example.com client
  for peer in 0 1; do
   copy admin cert node peerOrganizations org${org}.example.com peers peer${peer}
  done
  copy admin cert ca peerOrganizations org${org}.example.com
done
genmsp ordererOrganizations example.com orderers orderer. orderer.example.com orderer
genmsp ordererOrganizations example.com users Admin@ orderer.example.com client
copy admin cert node ordererOrganizations example.com orderers orderer orderer.example.com
copy_admin_cert_ca ordererOrganizations example.com
```

3. Copy the core.yaml and orderer.yaml files to the examples/e2e_cli directory.

cp ../../sampleconfig/core.yaml ../../sampleconfig/orderer.yaml .

4. Open both the **core.yaml** and **orderer.yaml** files in a text editor. Edit the BCCSP section in both files to use the following values.

```
BCCSP:
   Default: PKCS11
   PKCS11:
# TODO: The default Hash and Security level needs refactoring to be
# fully configurable. Changing these defaults requires coordination
# SHA2 is hardcoded in several places, not only BCCSP
Hash: SHA2
Security: 256
Library:
Label:
Pin:
SoftwareVerify: true
SensitiveKeys: true
#FileKeyStore:
# KeyStore:
```

- 5. Open the base/peer-base.yaml file in a text editor.
 - **a.** Add the following line to the Environment section:

```
CORE_PEER_BCCSP_PKCS11_PIN=userpin
```

b. Add a Volumes section with the following entries to the base of the Services section:

```
volumes:
- ../core.yaml:/etc/hyperledger/fabric/core.yaml
```

- 6. Open the base/docker-compose-base.yaml file in a text editor.
 - a. Add the following line to the Environment section of orderer.example.com:

```
- ORDERER_GENERAL_BCCSP_PKCS11_PIN=userpin
```

- **b.** Add the following line to the Volumes section of orderer.example.com:
 - ../orderer.yaml:/etc/hyperledger/fabric/orderer.yaml
- 7. Open the **docker-compose-cli.yaml** file in a text editor.
 - **a.** Add the following lines to the end of the **orderer.example.com** section:

```
environment:
- ORDERER_GENERAL_BCCSP_PKCS11_LABEL=orderer.example.com
- ORDERER_GENERAL_BCCSP_PKCS11_LIBRARY=
/etc/hyperledger/fabric/dpod/orderer.example.com/libs/64/libCryptoki2.so
- ChrystokiConfigurationPath=/etc/hyperledger/fabric/dpod/orderer.example.com
volumes:
- etc/hyperledger/fabric/dpod/orderer.example.com:
/etc/hyperledger/fabric/dpod/orderer.example.com
```

b. Add the following lines to the end of the **peer.0.org1.example.com** and **peer1.org1.example.com** sections:

```
environment:
- CORE_PEER_BCCSP_PKCS11_LABEL=org1.example.com
- CORE_PEER_BCCSP_PKCS11_LIBRARY=
/etc/hyperledger/fabric/dpod/org1.example.com/libs/64/libCryptoki2.so
```

```
- ChrystokiConfigurationPath=/etc/hyperledger/fabric/dpod/org1.example.com
volumes:
- /etc/hyperledger/fabric/dpod/org1.example.com:
/etc/hyperledger/fabric/dpod/org1.example.com
```

c. Add the following lines to the end of the **peer0.org2.example.com** and **peer1.org2.example.com** sections:

```
environment:
- CORE_PEER_BCCSP_PKCS11_LABEL=org2.example.com
- CORE_PEER_BCCSP_PKCS11_LIBRARY=
/etc/hyperledger/fabric/dpod/org2.example.com/libs/64/libCryptoki2.so
- ChrystokiConfigurationPath=/etc/hyperledger/fabric/dpod/org2.example.com
volumes:
- /etc/hyperledger/fabric/dpod/org2.example.com:
/etc/hyperledger/fabric/dpod/org2.example.com
```

- **d.** Add the following lines to the cli volumes section:
 - /etc/hyperledger/fabric/dpod:/etc/hyperledger/fabric/dpod
 - ./core.yaml:/etc/hyperledger/fabric/core.yaml
- 8. Open the **scripts/scripts.sh** file in a text editor.
 - a. Add the following lines to the setGlobals function after "if [\$1 -eq 0 -o \$1 -eq 1]; then":

```
export CORE_PEER_BCCSP_PKCS11_
LIBRARY=/etc/hyperledger/fabric/dpod/org1.example.com/libs/64/libCryptoki2.so
export CORE_PEER_BCCSP_PKCS11_PIN=userpin
export CORE_PEER_BCCSP_PKCS11_LABEL=org1.example.com
export ChrystokiConfigurationPath=/etc/hyperledger/fabric/dpod/org1.example.com
```

b. Add the following lines to the setGlobals function after "else":

```
export CORE_PEER_BCCSP_PKCS11_
LIBRARY=/etc/hyperledger/fabric/dpod/org2.example.com/libs/64/libCryptoki2.so
export CORE_PEER_BCCSP_PKCS11_PIN=userpin
export CORE_PEER_BCCSP_PKCS11_LABEL=org2.example.com
export ChrystokiConfigurationPath=/etc/hyperledger/fabric/dpod/org2.example.com
```

c. Add the following lines to the beginning of the checkOSNAvailability function:

```
export CORE_PEER_BCCSP_PKCS11_
LIBRARY=/etc/hyperledger/fabric/dpod/orderer.example.com/libs/64/libCryptoki2.so
export CORE_PEER_BCCSP_PKCS11_PIN=userpin
export CORE_PEER_BCCSP_PKCS11_LABEL=orderer.example.com
export ChrystokiConfigurationPath=/etc/hyperledger/fabric/dpod/orderer.example.com
```

9. Open the **generateArtifacts.sh** file in a text editor. Edit the bottom section of the file to use **gencerts.sh** to create key material. Modify the file so it appears as the following:

```
generateCerts
replacePrivateKey
./gencerts.sh
generateChannelArtifacts
```

10. Open the network_setup.sh file in a text editor. Comment the networkDown function so that artifacts are not deleted. Change:

```
rm -rf channel-artifacts/*.block channel-artifacts/*.tx crypto-config
to
# rm -rf channel-artifacts/*.block channel-artifacts/*.tx crypto-config
```

11. Enter the following command to run e2e cli.


./generateArtifacts.sh
./network_setup.sh up

About the Hyperledger Fabric CA Server

Hyperledger Fabric is a variant of the Hyperledger Blockchain project. Hyperledger Fabric allows for private and permissioned access, the members of the network must enroll through a Membership Service Provider (MSP).

Hyperledger Fabric has a ledger, uses smart contracts, and is a system that allows participants to manage their transactions. Ledger data can be stored in multiple formats, consensus mechanisms may be switched in and out, and multiple MSPs are supported. Hyperledger Fabric also offers the ability to create channels, allowing you to create a separate ledger of transactions.

The following diagram illustrates how the Hyperledger Fabric CA server fits into the overall Hyperledger Fabric architecture:



There are two methods of interacting with a Hyperledger Fabric CA server:

- > The Hyperledger Fabric CA client
- > The Hyperledger Fabric SDK

The Hyperledger Fabric CA client or SDK may connect to a server in a cluster of Hyperledger Fabric CA servers (see the Cluster of Fabric-CA Servers in the diagram). In this configuration the client routes to an HA proxy endpoint which load balances traffic to one of the fabric-ca-server cluster members.

A server may contain multiple CAs. Each CA is either a root CA or an intermediate CA. Each intermediate CA has a parent CA which is either a root CA or another intermediate CA.

All Hyperledger Fabric CA servers in a cluster share the same database for keeping track of identities and certificates. If an LDAP is configured the identity information is stored by the LDAP, rather than the database.