# Classes 14 & 15: Magnetism, Part 2 AP Physics

Dr. Timothy Leung

Olympiads School

February 2018

### Files for You to Download

#### Download from the school website:

1. 14-Magnetism2.pdf—The "print version" of this presentation. If you want to print the slides on paper, I recommend printing 4 slides per page.

Please download/print the PDF file before each class. When you are taking notes, pay particular attention to things I say that aren't necessarily on the slides.

# Magnetic Flux


**Question:** If a current-carrying wire can generate a magnetic field, can a magnetic field affect the current in a wire?

**Answer:** Yes, sort of...

To understand how to *induce* a curent by a magnetic field, we need to look at fluxes again.

# Magnetic Flux

Magnetic flux is defined as:



$$\Phi_{\text{magnetic}} = \int \mathbf{B} \cdot d\mathbf{A}$$

where  $\bf B$  is the magnetic field, and  $d{\bf A}$  is the infinitesimal area pointing **outwards**. If you are uncomfortable with using vector surfaces, note that magnetic flux can also be expressed as:

$$\Phi_{\rm magnetic} = \int \mathbf{B} \cdot \hat{\mathbf{n}} dA$$

where  $\hat{\bf n}$  is the outward normal direction

### Magnetic Flux Over a Closed Surface

The unit for magnetic flux is a "weber" (Wb), in honor of German physicist Wilhelm Weber, who invented the electromagnetic telegraph with Carl Gauss. It is defined as:

$$1 \,\mathrm{Wb} = 1 \,\mathrm{Tm}^2$$

The magnetic flux over a closed surface is always zero:

$$\oint \mathbf{B} \cdot d\mathbf{A} = 0$$

Since magnetic field lines only exist as a loop, that means there should be equal amount of "flux" flowing out of a closed surface as entering the surface.

# Changing Flux

We can

Unlike in a basic circuit, where the *emf* is concentrated at the terminals of the battery, the induced *emf* is spread across the entire wire.

# Faraday's Law

Faraday's law states that the rate of change of magnetic flux produces an electromotive force:

$$\mathcal{E} = \oint \mathbf{E} \cdot d\mathbf{l} = -\frac{d\Phi}{dt}$$

## How Can Magnetic Flux Change

Magnetic flux can change due to a number of reasons:

- 1. **Changing magnetic field strength** e.g. if **B** is created by a time dependent current source like an alternating current
- 2. Changing orientation of magnetic field because the surface area is moving (translation and/or rotation) relative to B
- 3. **Changing area** the surface area from which the flux is calculated is changing

### Self Inductance

A solenoid carrying a current generates a magnetic field; its strength given by Biot-Savart Law.

#### **MISSING DIAGRAM HERE!**

Since  $\mathbf{B} \propto I$ , the magnetic flux through the coil is therefore also proportional to I, i.e.:

$$\Phi_{\mathsf{magnetic}} = LI$$

where L is the called the **self inductance** of the coil.

### Self Inductance

For a solenoid, we can see that the self inductance is given by:

$$L = \frac{\Phi_{\text{magnetic}}}{I} = \mu_0 n^2 A l$$

where  $\mu_o$  is the magnetic permeability of free space, n is the number of coil turns per unit length, and A and l are the cross-section and length of the solenoid. (i.e. Al is the enclosed volume.)

### Self Inductance and Induced EMF

If the current changes, the magnetic flux changes as well, therefore inducing an electromotive force in the circuit! According Faraday's law:


$$\mathcal{E} = -\frac{d\Phi}{dt} = -L\frac{dI}{dt}$$

The self-induced emf is proportional to the rate of change of current.

### Mutual Inductance

### Circuits with Inductors

- ullet Coils and solenoids in circuits are known as "inductors" and have large self inductance L
- Self inductance prevents currents rising and falling instantaneously
- A basic circuit containing a resistor and an inductor is called an LR circuit:



### **Analyzing LR Circuits**

Applying Kirchkoff's voltage law:


$$\mathcal{E}_0 - IR - L\frac{dI}{dt} = 0$$

We follow the same procedure as charging a capacitor to find the time dependent current:

$$I = \frac{\mathcal{E}_0}{R} \left( 1 - e^{-Rt/L} \right)$$

The time constant for an LR circuit is

$$\tau = \frac{L}{R}$$





# Magnetic Energy

Just as a capacitor stores energy, the energy stored by an inductor carrying a current I in given by:

$$U_m = \frac{1}{2}LI^2$$

## Maxwell's Equations in Integral Form

James Clerk Maxwell recognized the relationship between electricity and magnetism, and combined the few laws into a unifying set of equations, now known as **Maxwell's equations** for electrodynamics:

By manipulating the equations, we can show the existence of a "electromagnetic wave" that travels at the speed of light.

## Maxwell's Equations in Differential Form