
$$V(k_0) = \sum_{t=0}^{\infty} \left[\beta^t \ln(1 - \alpha\beta) + \beta^t \alpha \ln k_t \right]$$

$$= \ln(1 - \alpha\beta) \mathbf{Physics}^t \left[\frac{1 - (\alpha\beta)^t}{1 - \alpha\beta} \ln \alpha\beta + \alpha^t \ln k_0 \right]$$

$$= \frac{\alpha}{1 - \alpha\beta} \ln k_0 + \frac{\mathbf{Ppsics}^t}{1 - \beta} + \alpha \ln(\alpha\beta) \sum_{t=0}^{\infty} \left[\frac{\beta^t}{1 - \alpha} - \frac{(\alpha\beta)^t}{1 - \alpha} \right]$$

$$= \frac{\alpha}{1 - \alpha\beta} \ln k_0 + \frac{\ln(1 - \alpha\beta)}{1 - \beta} + \frac{\alpha\beta}{(1 - \beta)(1 - \alpha\beta)} \ln(\alpha\beta)$$



Summary is the best way to say "Good Bye"

$$= \ln(k^{\alpha} - \alpha \beta k^{\alpha}) + \beta \left[\frac{\alpha}{1 - \alpha \beta} \ln \alpha \beta k^{\alpha} + A \right]$$

$$= \ln(1 - \alpha \beta) + \alpha \ln k + \beta \left[\frac{\alpha}{1 - \alpha \beta} \left[\ln \alpha \beta + \alpha \ln k \right] + k \right]$$

$$= \alpha \ln k + \frac{\alpha \beta}{1 - \alpha \beta} \alpha \ln k + \ln(1 - \alpha \beta) + \frac{\alpha \beta}{1 - \alpha \beta} \ln \alpha \beta + \beta A$$

$$= \frac{\alpha}{1 - \alpha \beta} \ln k + \ln(1 - \alpha \beta) + \frac{\alpha \beta}{1 - \alpha \beta} \ln \alpha \beta + \beta A$$

$$= \frac{\alpha}{1 - \alpha \beta} \ln k + (1 - \beta) A + \beta A \qquad \text{Editor: Yuyang Songsheng}$$

$$= \frac{\alpha}{1 - \alpha \beta} \ln k + (1 - \beta) A + \beta A \qquad \text{Date: March 30, 2017}$$

$$= \frac{\alpha}{1 - \alpha \beta} \ln k + A$$

所以, 左边 = 右边, 证毕。

Contents

1	The	Thermodynamics					
	1.1	Introd	luction to thermodynamics	3			
	1.2	Entrop	by formulation of thermodynamics	4			
		1.2.1	Property of entropy function	4			
		1.2.2	Simple problems	5			
		1.2.3	Heat and Work	6			
	1.3	Therm	nodynamic potential	8			
		1.3.1	Energy Scheme	8			
		1.3.2	Intensive Variables and Thermodynamic Potentials	8			
		1.3.3	Free Energy and Maxwell Relations	10			
		1.3.4	Gibbs Free Energy and Enthalpy	10			
		1.3.5	Other Thermodynamic Potentials	11			
	1.4	The Eu	ıler and Gibbs-Duhem Equations	12			
	1.5		nodynamic systems with multi-components	13			
		1.5.1	Chemical Reactions	13			
		1.5.2	Phase Coexistence	14			
		1.5.3	The Clausius-Clapeyron Equation	15			
		1.5.4	The Coexistence Curve	15			
		1.5.5	Coexistence of Several Phases	15			
		1.5.6	The Critical Point	16			
2	Principles of Statistical Mechanics and Ensembles						
	2.1	-	ty matrix	17			
	2.2		ical ensemble	18			
		2.2.1	Micro-canonical ensemble	18			
		2.2.2	Canonical ensemble	18			
		2.2.3	Grand-canonical ensemble	19			
	2.3	Fluctu	ations	20			
		2.3.1	Canonical Ensemble	20			
		2.3.2	Grand canonical ensemble	20			
3	Inte	raction-	-free Systems	22			
	3.1		al discussion	22			
		3.1.1	Bose-Einstein Statistics	22			
		3.1.2	Fermi-Dirac Statistics	23			
		3.1.3	Boltzmann Statistics	23			
	3.2	Ideal I	Boltzmann Gas	24			

Contents			
	3.2.1 Molecules without internal motion		24
	3.2.2 Molecules without internal motion		26
3.3	Ideal Bose Systems		27
3.4	Ideal Fermi systems		30
3.5	Thermodynamics of the blackbody radiation		34



Chapter 1 Thermodynamics

----(0/0/0)**---**

1.1 Introduction to thermodynamics

A thermodynamic system is a macroscopic system whose behaviour is identified thanks to a small and finite number of quantities - the thermodynamic properties.

There is a certain degree of circularity in the definition of thermodynamic parameters, which is resolved by experiment. One considers only a restricted set of manipulations on thermodynamic systems. In practice, one allows them to be put in contact with one another, or one acts upon them by changing a few macroscopic properties such as their volume or the electric or magnetic field in which they are immersed. One then identifies a number of properties such that, if they are known before the manipulation, their values after the manipulation can be predicted. The smallest set of properties that allows one to successfully perform such a prediction can be selected as the basis for a thermodynamic description of the system.

If the state of a thermodynamic system can be fully characterized by the values of the thermodynamic variables, and if these values are invariant over time, one says that it is in a state of thermodynamic equilibrium. Thermodynamic equilibrium occurs when all fast processes have already occurred, while the slow ones have yet to take place. Clearly the distinction between fast and slow processes is dependent on the observation time τ that is being considered.

A system can be shown to be in equilibrium if the observation time is fairly short, while it is no longer possible to consider it in equilibrium for longer observation times. A more curious situation is that the same system can be considered in equilibrium, but with different properties, for different observation times.

Let us consider two thermodynamic systems, 1 and 2, that can be made to interact with one another. Variables like the volume V, the number of particles N, and the internal energy U, whose value (relative to the total system) is equal to the sum of the values they assume in the single systems, are called additive or extensive. Strictly speaking, internal energy is not extensive, unless the interaction between 1 and 2 can be neglected.

The fundamental hypothesis of thermodynamics is that it should be possible to characterize the state of a thermodynamic system by specifying the values of a certain set (X_0, X_1, \cdots, X_r) of extensive variables. For example, X_0 could be the internal energy U, X_1 the number of particles N, X_2 the volume V of the system, and so on.

The central problem of thermodynamics is that given the initial state of equilibrium of sev-

eral thermodynamic systems that are allowed to interact, determine the final thermodynamic state of equilibrium.

The interaction between thermodynamic systems is usually represented by idealized walls that allow the passage of one (or more) extensive quantities from one system to the other. Among the various possibilities, the following are usually considered:

- Thermally conductive walls These allow the passage of energy, but not of volume or particles.
- **Semipermeable walls** These allow the passage of particles belonging to a given chemical species (and consequently also of energy)

The space of possible states of equilibrium (compatible with constraints and initial conditions) is called the space of virtual states. The initial state is obviously a (specific) virtual state. The central problem of thermodynamics can obviously be restated as follows:

Characterize the actual state of equilibrium among all virtual states.

1.2 Entropy formulation of thermodynamics

1.2.1 Property of entropy function

There exists a function S of the extensive variables (X_0, X_1, \dots, X_r) , called the entropy, that assumes the maximum value for a state of equilibrium among all virtual states and that possesses the following properties:

1. Extensivity: If 1 and 2 are thermodynamic systems, then

$$S^{(1\cup 2)} = S^{(1)} + S^{(2)}$$

2. **Convexity**: If $X^1 = (X_0^1, X_1^1, \dots, X_r^1)$ and $X^2 = (X_0^2, X_1^2, \dots, X_r^2)$ are two thermodynamic states of the same system, then for any a between 0 and 1, one obtains

$$S[(1-\alpha)X^1 + \alpha X^2] \ge (1-\alpha)S(X^1) + \alpha S(X^2)$$

From this expression, if we take the derivative with respect to α at $\alpha = 0$, we obtain

$$\sum_{i=0}^{r} \frac{\partial S}{\partial X_{i}} \bigg|_{X^{1}} (X_{i}^{2} - X_{i}^{1}) \ge S(X^{2}) - S(X^{1})$$

which expresses the fact that the surface $S(X_0, X_1, \dots, X_r)$ is always below the plane that is tangent to each of its points. (We adpot the convention that convex means upper convex).

3. **Monotonicity**: $S(U, X_1, \dots, X_r)$ is a monotonically increasing function of the internal energy U:

$$\left. \frac{\partial S}{\partial U} \right|_{X_1, \cdots, X_T} = \frac{1}{T} > 0$$



The entropy postulate allows one to solve the central problem of thermodynamics, by referring it back to the solution of a constrained extremum problem: The equilibrium state corresponds to the maximum entropy compatible with the constraints.

1.2.2 Simple problems

Thermal Contact

Let us consider two systems, 1 and 2, that are in contact by means of a thermally conductive wall. The virtual state space is therefore defined by the relations:

$$U^{(1)} + U^{(2)} = U = \text{const.}$$

$$X_i^{(1)} = \text{const.}$$
 $X_i^{(2)} = \text{const.}$ $r = 1, \dots, r$

Let us look for the maximum of S as a function of $U^{(1)}$:

$$\frac{\partial S}{\partial U^{(1)}} = \frac{\partial S^{(1)}}{\partial U^{(1)}} \bigg|_{U^{(1)}} - \frac{\partial S^{(2)}}{\partial U^{(2)}} \bigg|_{U-U^{(1)}}$$

If we denote the value of $U^{(1)}$ at equilibrium by $U^{(1)}_{\mathrm{eq}}$, then we have

$$\left.\frac{\partial S^{(1)}}{\partial U^{(1)}}\right|_{U_{\mathrm{eq}}^{(1)}} = \left.\frac{\partial S^{(2)}}{\partial U^{(2)}}\right|_{U_{\mathrm{eq}}^{(2)}}$$

Due to entropy's convexity, we can futher derive that

$$\left[\frac{\partial S^{(1)}}{\partial U^{(1)}} \Big|_{U_{\text{in}}^{(1)}} - \left. \frac{\partial S^{(2)}}{\partial U^{(2)}} \right|_{U_{\text{in}}^{(2)}} \right] (U_{\text{eq}}^{(1)} - U_{\text{in}}^{(1)}) \ge 0$$

Let us introduce the quantity

$$T = \left(\frac{\partial S}{\partial U}\right)^{-1}$$

According to our hypotheses, this quantity is positive. We obtained the following results:

- ullet At equilibrium, T is the same in all subsystems that are in reciprocal contact by means of thermally conductive walls.
- In order to reach equilibrium, energy shifts from systems with higher values of T toward systems with lower values of T.

Later, we will show that T is the temperature of the system.

A Thermally Conductive and Mobile Wall

In this case, the two systems can also exchange volume V, in addition to internal energy U. If we introduce the quantity p by

$$\frac{p}{T} = \frac{\partial S}{\partial V}$$



The two equilibrium conditions are

$$T^{(1)} = T^{(2)} \quad p^{(1)} = p^{(2)}$$

One can easily prove that between two systems, both initially at the same temperature, volume is initially released by the system in which p is lower to the system in which p is higher. Later, we will show that p is the pressure of the system.

A Semipermeable Wall

Let us consider a system composed of several chemical species, and let us introduce the number of molecules N_1, \dots, N_r belonging to the chemical species that constitute it as part of the thermodynamic variables. Let us suppose that two systems of this type are separated by a wall that only allows the k-th chemical species to pass. Clearly, it is impossible for the exchange of molecules to occur without an exchange of energy. If we introduce the quantity μ_i by

$$\frac{\mu_i}{T} = \frac{\partial S}{\partial N_i}$$

The equilibrium conditions will therefore be

$$T^{(1)} = T^{(2)} \quad \mu^{(1)} = \mu^{(2)}$$

We will define μ_i as the chemical potential of the specie *i*.

1.2.3 Heat and Work

From mechanics (and from electromagnetism), we can derive an expression for the infinitesimal mechanical work performed on the system by varying the extensive quantities. One usually adopts a sign convention according to which work is considered positive if the system performs work on the outside. Following this convention, the expression of infinitesimal work is given by

$$\delta W = -\sum_{i=1}^{r} f_i dX_i$$

On the one hand, we have

$$dS = \frac{dU}{T} + \sum_{i=1}^{r} \left. \frac{\partial S}{\partial X_i} \right|_{U, \dots, X_r} dX_i$$

It can be written as

$$dU = TdS - \sum_{i=1}^{r} T \frac{\partial S}{\partial X_i} \bigg|_{U, \dots, X_r} dX_i$$

On the other hand, we have

$$dU = \delta Q - \delta W$$

So we can get

$$\delta Q = T dS \quad \left. \frac{\partial S}{\partial X_i} \right|_{U,\cdots,X_r} = -\frac{f_i}{T}$$



Temperature

Let us consider a system made up of a thermal engine and two heat reservoirs with $T_1 > T_2$. A heat reservoir is a system for which T is independent of U. The whole compound system is enclosed in a container that allows it to exchange energy with the environment only in a purely mechanical way.

Let the system evolve from an initial equilibrium condition, in which the first heat reservoir has internal energy U_1 , the second has internal energy U_2 , and the thermal engine is in some equilibrium state, to a final equilibrium state in which the first heat reservoir has internal energy U_1' , the second has U_2' . So $W=(U_1+U_2)-(U_1'+U_2')$, and the thermal engine is back to its initial state. By definition, the efficiency of the engine is given by $\eta=\frac{W}{U_1-U_1'}$.

In a transformation of this kind, the total entropy of the compound system cannot become smaller. Thus, we have

$$S^{(1)}(U_1) + S^{(2)}(U_2) \le S^{(1)}(U_1') + S^{(2)}(U_2')$$

On the other hand, since we are dealing with heat reservoirs, we have

$$S^{(i)}(U_i') = S^{(i)}(U_i) + \frac{U_i' - U_i}{T_i}$$
 $i = 1, 2$

Thus, we have

$$\frac{U_1 - U_1'}{T_1} \le \frac{U_2' - U_2}{T_2}$$

Therefore,

$$\eta \le 1 - \frac{T_2}{T_1}$$

Compared with the maximum efficiency evaluated in elementary thermodynamics, we can conclude that T is the absolute temperature, up to an overall factor, which can be fixed to 1 by rescaling the S.

Pressure

Let us consider an infinitesimal variation of V. In this case, mechanics tells us that the work performed by the system is given by $\delta W = P dV$. So we have

$$\left. \frac{\partial S}{\partial V} \right|_{U, \cdots, X_T} = \frac{P}{T}$$

This allows us to identify the pressure P with the quantity p we defined previousl.

The Fundamental Equation

The equation

$$S = S(X_0 = U, X_1, \cdots, X_r)$$

is called the fundamental equation, and it represents a complete description of the thermodynamics of the system being considered.



1.3 Thermodynamic potential

1.3.1 Energy Scheme

We can also use a different (but equivalent) formulation of the fundamental principle of thermodynamics, in which entropy assumes the role of an independent variable, while energy becomes a dependent variable that satisfies a variational principle. This formalism is known as the energy scheme. In this formalism, the maximum entropy principle is replaced by the principle of minimum internal energy:

Among all states with a specific entropy value, the state of equilibrium is that in which internal energy is minimal.

Let ΔX be a virtual variation of the extensive variables (excluding internal energy U) with respect to the equilibrium value $X_{\rm eq}$. Then

$$\Delta S = S(U, X_{\text{eq}} + \Delta X) - S(U, X_{\text{eq}}) \le 0$$

Since S is a monotonically increasing function of U, there exists a value U'>U such that $S(U',X_{\rm eq}+\Delta X)=S(U,X_{\rm eq})$. Therefore, if S is kept constant, as the system moves out of equilibrium, U cannot but increase. This is what we wanted to prove.

Therefore, the fundamental equation in the energy scheme is

$$U = U(S, X_1, \cdots, X_r)$$

U's differential assumes the form

$$dU = TdS + \sum_{i=1}^{r} f_i dX_i$$

Further more, we can derive that

$$U[(1-\alpha)Y^1 + \alpha Y^2] \le (1-\alpha)U(Y^1) + \alpha U(Y^2)$$

which implies that the internal energy function is concave.

1.3.2 Intensive Variables and Thermodynamic Potentials

The derivatives $f_i = \frac{\partial U}{\partial X_i}$ of the internal energy U with respect to extensive quantities S, $\{X_i\}$ are called intensive quantities. For uniformity's sake, we define $f_0 \equiv \frac{\partial U}{\partial X_i} = T$. A given quantity f_i is called the conjugate of the corresponding variable X_i , and vice versa. The temperature T and entropy S are therefore conjugates, as are the pressure (with the opposite sign) -P and the volume V.

Since both U and X_i are extensive, in a homogeneous system, intensive variables are not dependent on system size. Moreover, if a system is composed of several subsystems that can exchange the extensive quantity X_i , the corresponding intensive variable f_i assumes the same value in those subsystems that are in contact at equilibrium.



We now want to identify the state of equilibrium among all states that exhibit a given value of an intensive variable f_i . Specifically, for i = 0, we are confronted with the case of system with a fixed temperature, i.e. heat reservoir.

Let us now define the Helmholtz free energy F(T, X) by the relation

$$F(T,X) = U(S(T,X),X) - TS(T,X)$$

where $X = \{X_1, \dots, X_r\}$. We can then show that the thermodynamical equilibrium in these conditions is characterized by the following variational principle:

The value of the Helmholtz free energy is minimal for the equilibrium state among all virtual states at the given temperature T.

Let us now consider more generally the Legendre transform of the internal energy U with respect to the intensive variable f_i :

$$\Phi(S, f_1, X_2, \cdots, X_r) = U(S, X_1(S, f_1, X_2, \cdots, X_r), X_2, \cdots, X_r) - f_1 X_1(S, f_1, X_2, \cdots, X_r)$$

where $X_1(S,f_1,X_2,\cdots,X_r),X_2,\cdots,X_r)$ is determined by the condition

$$f_1 = \left. \frac{\partial U}{\partial X_1} \right|_{S(X_2, \dots, X_n)}$$

Then, the state of equilibrium is specified by the following criterion:

Among all the states that have the same value as f_1 , the state of equilibrium is that which corresponds to the minimum value of Φ .

Let us observe that the partial derivative of Φ , performed with respect to f_1 , with the other extensive variables kept fixed, yields the value of the extensive variable X_1 :

$$\frac{\partial \Phi}{\partial f_1}\Big|_{S, X_2, \dots, X_r} = -X_1(S, f_1, X_2, \dots, X_r)$$

Nothing prevents us from considering two or more intensive variables as fixed—for example, $f_0 = T$ and f_1 . Similar considerations will then lead us to introduce the thermodynamic potential $\Phi(T, f_1, X_2, \dots, X_r)$, obtained as a Legendre transform of U with respect to S and X_1 :

$$\Phi(T, f_1, X_2, \cdots, X_r) = U - TS - f_1 X_1$$

This thermodynamic potential assumes at equilibrium the minimum value among all the states with the same values of T and f_1 . We can therefore obtain a whole series of thermodynamic potentials, by using a Legendre transform with respect to the extensive variables X_i . We cannot however eliminate all extensive variables in this manner. We will see later that if we did this, the resulting thermodynamic potential would identically vanish. For the time being, it is sufficient to observe that the Φ potentials are extensive quantities, and one cannot see how they could



be a function only of intensive quantities like the f_i . A general thermodynamic potential

$$\Phi(S, f_1, \dots, f_k, X_{k+1}, \dots, X_r) = U - \sum_{i=1}^k f_i X_i$$

is concave as a function of the remaining extensive variables, for fixed values of the intensive variables f_1, \dots, f_k . Φ on the other hand is convex as a function of the intensive variables f_i s, when the extensive variables are fixed.

1.3.3 Free Energy and Maxwell Relations

The natural variables of F are the temperature T and the extensive variables X_1, \dots, X_r , entropy excluded. Entropy can be obtained by taking the derivative of F with respect to T. The expression for the differential of F is

$$dF = -SdT + \sum_{i=1}^{r} f_i dX_i$$

More specifically, by setting $X_1 = V$, one has

$$-P = \left. \frac{\partial F}{\partial V} \right|_{T, X_2, \cdots, X_r}$$

If we now take this equation's derivative with respect to T and we use the theorem of the equality of mixed derivatives, we obtain

$$-\frac{\partial P}{\partial T}\Big|_{V,X_2,\cdots,X_r} = -\frac{\partial^2 F}{\partial T \partial V} = -\frac{\partial S}{\partial V}\Big|_{T,X_2,\cdots,X_r}$$

These relations between thermodynamic derivatives that derive from the equality of mixed derivatives of thermodynamic potentials are called Maxwell relations.

The free energy designation is derived from the following property. If a system is put in contact with a reservoir at temperature T, we can prove the maximum quantity of work $W_{\rm max}$ that it can perform on its environment is equal to the variation in free energy between the initial and final states. In other words, one has

$$W \le F_{\rm in} - F_{\rm fin}$$

1.3.4 Gibbs Free Energy and Enthalpy

Transforming F according to Legendre with respect to V, we obtain a new thermodynamic potential, called the Gibbs free energy:

$$G(T, P, X_2, \cdots, X_r) = F + PV = U - TS - PV$$



The variational principle satisfied by the Gibbs free energy is the following:

Among all states that have the same temperature and pressure values, the state of equilibrium is that in which the Gibbs free energy assumes the minimum value.

G's differential is expressed as follows:

$$dG = -SdT + VdP + \sum_{i=2}^{r} f_i dX_i$$

We can prove that if a system is brought toward equilibrium while temperature and pressure are kept constant, the maximum work that can be performed on its environment is given precisely by the difference between the initial and final values of G.

If on the other hand, we Legendre transform the internal energy U with respect to V, we obtain a new thermodynamic potential, usually denoted by H and called enthalpy:

$$H(S, P, X_2, \cdots, X_r) = U + PV$$

Enthalpy governs the equilibrium of adiabatic processes that occur while pressure is constant: Among all states that have the same entropy and pressure values, the state of equilibrium is the one that corresponds to the minimum value of enthalpy.

If a system relaxes toward equilibrium while the pressure is kept constant, the maximum heat that can be produced by the system is equal to its variation in enthalpy. For this reason, enthalpy it is also called free heat. The differential of H is given by $dH = TdS + VdP + \sum_{i=2}^{r} f_i dX_i$

The equality of the mixed derivatives of G and H yield two more Maxwell relations:

$$-\frac{\partial S}{\partial P}\bigg|_{T,X_2,\cdots,X_r} = \frac{\partial V}{\partial T}\bigg|_{P,X_2,\cdots,X_r}$$
$$\frac{\partial T}{\partial P}\bigg|_{S,X_2,\cdots,X_r} = \frac{\partial V}{\partial S}\bigg|_{P,X_2,\cdots,X_r}$$

1.3.5 Other Thermodynamic Potentials

The Legendre transform of F with respect to N produces a thermodynamic potential (often written as Ω) that depends on T, on volume V, on chemical potential μ , and on the other extensive variables:

$$\Omega(T, V, \mu) = F - \mu N$$

Its differential is expressed as follows:

$$d\Omega = -SdT - PdV - Ndu$$

If one transforms U instead, one obtains a rarely used potential that depends on S, V, and μ , which we will designate as Φ :

$$\Phi(S, V, \mu) = U - \mu N$$



Its differential is given by

$$d\Phi = TdS - PdV - Nd\mu$$

We have the following Maxwell relations

$$\left.\frac{\partial S}{\partial \mu}\right|_{T,V} = \left.\frac{\partial N}{\partial T}\right|_{\mu,V}$$

$$\left. \frac{\partial S}{\partial N} \right|_{T,V} = -\left. \frac{\partial \mu}{\partial T} \right|_{N,V}$$

1.4 The Euler and Gibbs-Duhem Equations

$$U(\lambda S, \lambda X_1, \cdots, \lambda X_r) = \lambda U(S, X_1, \cdots, X_r)$$

By taking the derivative of this equation with respect to λ and setting $\lambda=1$, we obtain the Euler equation

$$TS + \sum_{i=1}^{r} f_i X_i = U$$

More particularly, for simple fluids, one obtains

$$U = TS - PV + \mu N$$

which among other things implies that

$$\mu = (U - TS + PV)/N = G/N$$

$$\Omega = U - TS - \mu N = -PV$$

More particularly, from the Euler equation, it follows that the Legendre transform of U with respect to all extensive variables vanishes identically. Let us note that the interpretation of the chemical potential as a per particle density of Gibbs free energy is valid only in the case of simple fluids—in the case of a mixture of several chemical species, it is no longer valid. If we take the Euler equation's differential, we obtain

$$dU = TdS + SdT + \sum_{i=1}^{r} f_i dX_i + X_i df_i$$

By subtracting both sides of this equation from the usual expression of dU, we obtain the Gibbs-Duhem equation:

$$SdT + \sum_{i=1}^{r} X_i df_i = 0$$

In the case of simple fluids, for example, one arrives at

$$SdT - VdP + Nd\mu = 0$$



By dividing with respect to the number of particles N, one obtains the Gibbs-Duhem equation in the form

$$d\mu = vdP - sdT$$

where v represents volume per particle and s entropy per particle.

Relations between the densities and the intensive variables obtained by deriving the fundamental equation are called equations of state. If, for example, we consider the Gibbs free energy for a simple fluid, we arrive at

$$V = \left. \frac{\partial G}{\partial P} \right|_{T.N}$$

from which we obtain

$$v = \frac{V}{N} = v(P, T)$$

where we have made use of the fact that G is extensive, and therefore proportional to N. In the case of the simple fluid, we have another independent equation of state:

$$s = \frac{S}{N} = -\frac{1}{N} \left. \frac{\partial G}{\partial T} \right|_{P}$$

which expresses the entropy per particle s as a function of P and T. In reality, the two equations of state are not completely independent, because of the Maxwell relations:

$$-\frac{\partial s}{\partial P}\bigg|_{T} = \left. \frac{\partial v}{\partial T} \right|_{P}$$

The ideal gas is a simple fluid that satisfies the equation of state

$$P = \frac{NT}{V}$$

Maxwell relations allow us to prove that in an ideal gas, the internal energy only depends on N and T (and not on the volume V). Moreover, entropy is the sum of a term that depends only on T with one that depends only on V.

1.5 Thermodynamic systems with multi-components

1.5.1 Chemical Reactions

Let us now consider a mixture of r chemical species, A_1, \dots, A_r , which can be transformed into one other by a reaction of the following type:

$$\nu_1 A_1 + \dots + \nu_k A_k \leftrightarrows \nu_{k+1} A_{k+1} + \dots + \nu_r A_r$$

We can conventionally assign negative stoichiometric coefficients to the products, so as to write this formula as a formal equation:

$$\sum_{i=1}^{r} \nu_i A_i = 0$$



If temperature and pressure are kept fixed, we can calculate the variation of Gibbs free energy for a certain variation in the number of particles due to the reaction

$$\delta G = \sum_{i} \frac{\partial G}{\partial N_{i}} \bigg|_{P,T} \delta N_{i} \propto \sum_{i} \frac{\partial G}{\partial N_{i}} \bigg|_{P,T} \nu_{i} = \sum_{i} \mu_{i} \nu_{i}$$

Since at equilibrium one must have $\delta G = 0$ for any virtual variation of the N_i , one will have

$$\sum_{i} \mu_{i} \nu_{i} = 0$$

where the stoichiometric coefficients ν_i are taken with their corresponding signs.

1.5.2 Phase Coexistence

It frequently happens that two systems characterized by different thermodynamic density values can maintain thermodynamic equilibrium even in the absence of constraints on the mutual exchange of extensive quantities. This situation is called phase coexistence.

In the case of a simple fluid, it is realized, for example, when a liquid coexists with its vapor inside a container. In this case, the intensive variables assume the same value in both systems, while densities assume different values. In these cases, we refer to each of the coexisting homogeneous systems as a phase.

One can describe phase coexistence by saying that the equation of state

$$v = v(P, T)$$

does not admit of a unique solution, but instead allows for at least the two solutions $v=v_{\rm liq}$ and $v=v_{\rm vap}$ which correspond to the liquid and vapor, respectively.

Since the liquid and vapor coexist and can exchange particles, the chemical potential of the liquid has to be equal to that of the vapor:

$$\mu_{\text{liq}}(P,T) = \mu_{\text{vap}}(P,T)$$

On the other hand, we know that for a simple fluid, the chemical potential is equal to the Gibbs free energy per particle. We can verify that the Gibbs free energy in the total system does not depend on the number of particles that make up the liquid and the vapor system:

$$G = G_{\text{liq}} + G_{\text{vap}} = N_{\text{liq}}\mu_{\text{liq}} + N_{\text{vap}}\mu_{\text{vap}} = (N_{\text{liq}} + N_{\text{vap}})\mu = N\mu$$

The volume per particle of the system is given by

$$v = \frac{V_{\text{liq}} + V_{\text{vap}}}{N} = \frac{N_{\text{liq}}v_{\text{liq}} + N_{\text{vap}}v_{\text{vap}}}{N} = x_{\text{liq}}v_{\text{liq}} + x_{\text{vap}}v_{\text{vap}}$$

where $x_{\rm liq}$ is the fraction of particles in the liquid and $x_{\rm vap}=1-x_{\rm liq}$ that of the particles in the vapor. As a consequence, the value of v lies somewhere between $v_{\rm liq}$ and $v_{\rm vap}$.



1.5.3 The Clausius-Clapeyron Equation

If we consider a thermodynamic system as a function of its intensive variables, we can identify some regions in which the thermodynamic properties vary regularly with variations of their values. These regions represent thermodynamically stable phases and are limited by curves that represent phase transitions. The phase transitions can be discontinuous, like the phase coexistence we just discussed, or continuous. In the first case, the densities present a discontinuity at the transition, while in the second, they vary with continuity, even though their derivatives can exhibit some singularities. One often also employs the following terminology: discontinuous transitions are called first order transitions, while continuous ones are called second order transitions.

In the case of a simple fluid, it is possible to identify the transition curve within the plane of the intensive variables (P,T) - in other words, the curve $P=P_t(T)$ - from the condition of equality of the chemical potential μ between the two coexisting phases:

$$\mu_{\text{lig}}(P_t(T), T) = \mu_{\text{vap}}(P_t(T), T)$$

The pressure $P_t(T)$ at which the transition occurs is also called vapor pressure. It is possible to relate this curve locally with the discontinuity of densities at transition. To obtain this relation, let us take the total derivative of this equation with respect to T, along the transition line $P_t(T)$. We obtain

 $\frac{\partial \mu_{\text{liq}}}{\partial P} \bigg|_{T} \frac{dP_{t}}{dT} + \frac{\partial \mu_{\text{liq}}}{\partial T} \bigg|_{P} = \frac{\partial \mu_{\text{vap}}}{\partial P} \bigg|_{T} \frac{dP_{t}}{dT} + \frac{\partial \mu_{\text{vap}}}{\partial T} \bigg|_{P}$

Therefore,

$$\frac{dP_t}{dT} = \frac{s_{\text{vap}} - s_{\text{liq}}}{v_{\text{vap}} - v_{\text{liq}}}$$

This equation, which can be applied to each case of phase coexistence, is called the Clausius - Clapeyron equation.

1.5.4 The Coexistence Curve

We can represent the phase diagram in the plane (v,T), in which the intensive variable T is accompanied by the density v, the volume per particle. In this manner, phase coexistence is represented by the existence of a forbidden region $v_{\rm liq}(T) < v < v_{\rm vap}(T)$ in the plane. Outside this region, it is possible to obtain any given value of v in a homogeneous system. Within this region, instead, the system separates into a liquid and a vapor phase. The $x_{\rm liq}$ fraction of particles in the liquid phase (and the analogous fraction in the vapor phase) are determined by the condition that the entire system's volume per particle be equal to v. One thus obtains

$$x_{\rm liq} = \frac{v_{\rm vap} - v}{v_{\rm vap} - v_{\rm liq}}$$

This result is known as the lever rule.

1.5.5 Coexistence of Several Phases

Let us now consider a mixture of particles belonging to r different chemical species. Let us suppose that we are looking for the coexistence of q phases. At equilibrium, all the intensive



variables must assume the same value in the coexisting phases. We will therefore have a specific value for the pressure and the temperature, and in addition the chemical potential of each species will have to assume the same value in all the different phases. If we denote the chemical potential of species i in phase α as μ_i^{α} , we will then have

$$\mu_i^{\alpha} = \mu_i \quad i = 1, \cdots, r \quad \alpha = 1, \cdots,$$

In this equation, μ_i is the shared value taken by the chemical potential of species i. We thus obtain r(q-1) equations for q(r-1)+2 unknown values. These unknown values are P,T, and the q(r-1) independent densities x_i^α of species i in phase α . Generically speaking, therefore, f=2-q+r free parameters remain. For f=0, coexistence will occur in isolated points of the phase diagram, for f=1, along a line, and so on. The quantity f is called variance. It is called the Gibbs phase rule.

1.5.6 The Critical Point

Let us once again consider the simple fluid and observe that the coexistence of liquid and vapour cannot be obtained for temperatures higher than a certain temperature T_c , called the critical temperature. To be more precise, the transition curve ends at a point (P_c, T_c) , where P_c is the critical pressure. For $T < T_c$, the difference $v_{\rm vap} - v_{\rm liq}$ tends continuously toward zero when T gets close to T_c - the discontinuity of thermodynamic densities tends to vanish, or in other words, the transition goes from being discontinuous to being continuous (and finally to disappear at higher temperatures).

The critical point is a thermodynamic state with exceptional properties. For example, since for $T < T_c$ and $P = P_t(T)$ one gets $\partial P/\partial V|_T = 0$ (within the coexistence curve), this relation must ultimately be valid also at the critical point - in other words, the system's compressibility diverges:

$$\chi = -\frac{1}{V} \left. \frac{\partial V}{\partial P} \right|_T \to \infty \text{ for } T \to T_c$$

Various thermodynamic properties exhibit analogous singularities.



Chapter 2

Principles of Statistical Mechanics and Ensembles



2.1 Density matrix

In quantum mechanics, the state of a system is a vector in Hilbert space, denoted as $|\psi\rangle$. A physical observable is an operator on this Hilbert space, denoted as O. The expectation value of the measurement of the observable is $\langle\psi|O|\psi\rangle$. It is easy to verify that

$$\langle \psi | O | \psi \rangle = \text{Tr}(|\psi\rangle \langle \psi | O)$$

Now, consider a system whose space of states is the direct product of two subspace, i.e.

$$\mathcal{H} = \mathcal{H}_A \otimes \mathcal{H}_B$$

An arbitrary state can be decomposed as

$$|\psi\rangle = C_{iI}|i\rangle_A \otimes |I\rangle_B$$

So, we have

$$|\psi\rangle\langle\psi| = C_{iI}C_{jJ}^*|i,I\rangle\langle j,J|$$

We define the partial trace of $|\psi\rangle\langle\psi|$ on B as

$$\operatorname{Tr}_B(|\psi\rangle\langle\psi|) \equiv \sum_I C_{iI} C_{jI}^* |i\rangle\langle j|$$

It is an operator on \mathcal{H}_A . Now, suppose there is an observable which measures only on A, i.e.

$$\langle i, I|O|j, I\rangle = \delta_{IJ}\langle i|O_A|j\rangle$$

where O_A is an operator on \mathcal{H}_A . We can verify that

$$\langle \psi | O | \psi \rangle = \text{Tr}(|\psi\rangle\langle\psi|O) = \text{Tr}_A \left[\text{Tr}_B(|\psi\rangle\langle\psi|)O_A\right]$$

Now, if we take A as the system and B the environment, a piratical observable measures only on system. For any system which is coupled to environment, its state can be described by an operator

$$\rho = \text{Tr}_{\text{env}}(|\psi\rangle\langle\psi|)$$

So the expectation value of the measurement on the system is

$$\text{Tr}[\rho O_{\text{sys}}]$$

We can verify that

$$\operatorname{Tr}\rho = 1, \quad \rho^{\dagger} = \rho$$

and any eigenvalue of ρ must lie between 0 and 1. Suppose rho can be diagonalized as

$$\rho = \sum_{i} p_{i} |i\rangle\langle i|$$

We have

$$Tr[\rho O] = p_i \langle i|O|i\rangle$$

So it is reasonable to assume p_i as the (classical) probability of the system in (pure) state $|i\rangle$. One fundamental postulate of statistical mechanics is that the entropy operator of the system is

$$\hat{S} = -\ln \rho$$

So, the expectation value of entropy is

$$S = \text{Tr}[-\rho \ln \rho]$$

2.2 Statistical ensemble

2.2.1 Micro-canonical ensemble

Micro-canonical ensemble describes a system which is weakly coupled to the environment. The volume V and the number of the particles N are fixed. The energy of the system lies in a narrow range between $E-\Delta E$ and $E+\Delta E$. The total number of distinct microstates accessible to a system is then denoted by the symbol $\Gamma(V,N,E;\Delta)$ and, by assumption, any one of these microstates is as likely to occur as any other.

Accordingly, the density matrix in the energy representation will be of the form

$$\rho_{mn} = \rho_m \delta_{mn}$$

with

$$\rho_n = \begin{cases} 1/\Gamma \text{ for each of the accessible states} \\ 0 \text{ for all other states} \end{cases}$$

The entropy of the system is

$$S = \ln \Gamma$$

2.2.2 Canonical ensemble

Canonical ensemble describes a system which can exchange energy with the environment. The density matrix of the system is

$$\rho = \frac{e^{-\beta H}}{\text{Tr}[e^{-\beta H}]}$$

Now, we define

$$Z(\beta, V, N) \equiv \text{Tr}[e^{-\beta H}] \quad F(\beta, V, N) \equiv -\ln Z/\beta$$



The energy of the system is

$$U = \text{Tr}[\rho H] = -\left. \frac{\partial \ln Z}{\partial \beta} \right|_{V.N}$$

If we further define $T \equiv 1/\beta$, we have

$$U = F - T \left. \frac{\partial F}{\partial T} \right|_{VN}$$

The entropy of the system is

$$S = \text{Tr}[-\rho \ln \rho] = \frac{U - F}{T}$$

We can further derive that

$$\left. \frac{\partial U}{\partial S} \right|_{VN} = T$$

Now, we can identify T as the absolute temperature and F as free energy in thermodynamics.

2.2.3 Grand-canonical ensemble

Grand canonical ensemble describes a system which can exchange energy and particles with the environment. The density matrix of the system is

$$\rho = \frac{e^{-\beta(H-\mu N)}}{\text{Tr}[e^{-\beta(H-\mu N)}]}$$

Now, we define

$$Z_{\Omega}(\beta, V, \mu) \equiv \text{Tr}[e^{-\beta(H-\mu N)}] \quad \Omega(\beta, V, N) \equiv -\ln Z_{\Omega}/\beta$$

The particle number of the system is

$$N = \text{Tr}[\rho N] = \frac{1}{\beta} \left. \frac{\partial \ln Z_{\Omega}}{\partial \mu} \right|_{V,\beta} = -\left. \frac{\partial \Omega}{\partial \mu} \right|_{V,T}$$

We also have

$$U - \mu N = -\left. \frac{\partial \ln Z_{\Omega}}{\partial \beta} \right|_{V,\mu} = \Omega - T \left. \frac{\partial \Omega}{\partial T} \right|_{V,\mu}$$

The entropy of the system is

$$S = \text{Tr}[-\rho \ln \rho] = \frac{U - \mu N - \Omega}{T}$$

We can further derive that

$$\left. \frac{\partial U}{\partial N} \right|_{VS} = \mu$$

Now, we can identify μ as the chemical potential and Ω as grand canonical potential in thermodynamics.



2.3 Fluctuations –21/34–

2.3 Fluctuations

2.3.1 Canonical Ensemble

The density matrix for canonical ensemble is

$$\rho = \frac{e^{-\beta H}}{\text{Tr}[e^{-\beta H}]}$$

We have

$$\left. \frac{\partial \rho}{\partial \beta} \right|_{NV} = -\rho H + \rho \text{Tr}[\rho H]$$

Since $U = \text{Tr}[\rho H]$, we can derive that

$$\left. \frac{\partial U}{\partial \beta} \right|_{N,V} = -\text{Tr}[\rho H^2] + (\text{Tr}[\rho H])^2 = -\langle E^2 \rangle + \langle E \rangle^2 = -\langle (\Delta E)^2 \rangle$$

So, the relative fluctuation of energy in canonical ensemble is

$$\frac{\sqrt{\langle (\Delta E)^2 \rangle}}{\langle E \rangle} = \frac{T}{U} \sqrt{\frac{\partial U}{\partial T}}\Big|_{N,V} = T \frac{\sqrt{C_V}}{T} \sim O(N^{-1/2})$$

For large N (which is true for every statistical system) the relative r.m.s. fluctuation in the values of E is quite negligible.

2.3.2 Grand canonical ensemble

Density and energy fluctuations in the grand canonical ensemble is much more complicated. The detailed discussion can be found in section 4.5 of *Statistical Mechanics (R.K.Pathria & Paul D.Beale)*.

The density fluctuation is

$$\frac{\langle (\Delta n)^2 \rangle}{\langle n \rangle^2} = \frac{T}{V} \kappa_T$$

where $n=\frac{N}{V}$ is the number density and $\kappa_T=-\frac{1}{v}\left.\frac{\partial v}{\partial P}\right|_T$ is the isothermal compressibility of the system.

Thus, the relative root-mean-square fluctuation in the particle density of the given system is ordinarily $O(N^{-1/2})$ and, hence, negligible. However, there are exceptions, like the ones met with in situations accompanying phase transitions. In those situations, the compressibility of a given system can become excessively large, as is evidenced by an almost "flattening" of the isotherms. In the region of phase transitions, especially at the critical points, we encounter unusually large fluctuations in the particle density of the system. Such fluctuations indeed exist and account for phenomena like critical opalescence. It is clear that under these circumstances the formalism of the grand canonical ensemble could, in principle, lead to results that are not necessarily identical to the ones following from the corresponding canonical ensemble. In such cases, it is the formalism of the grand canonical ensemble that will have to



be preferred because only this one will provide a correct picture of the actual physical situation.

The energy fluctuation in grand canonical ensemble is

$$\langle (\Delta E)^2 \rangle = T^2 C_V + \left(\frac{\partial U}{\partial N} \Big|_{T,V} \right)^2 \langle (\Delta N)^2 \rangle$$

The mean-square fluctuation in the energy of a system in the grand canonical ensemble is equal to the value it would have in the canonical ensemble plus a contribution arising from the fact that now the particle number N is also fluctuating. Again, under ordinary circumstances, the relative root-mean-square fluctuation in the energy density of the system would be practically negligible. However, in the region of phase transitions, unusually large fluctuations in the value of this variable can arise by virtue of the second term in the formula.



Chapter 3 Interaction-free Systems



3.1 General discussion

3.1.1 Bose-Einstein Statistics

If the system is composed of interaction-free Bosons, the state of the system can be denoted as

$$|n_1, n_2, \cdots, n_i, \cdots\rangle$$

where n_i is the number of particles in state $|i\rangle$. Here, we choose $|i\rangle$ to the energy eigenstate with energy ϵ_i .

If we adopt grand-canonical ensemble, we have

$$Z_{\Omega} = \text{Tr}[e^{-\beta(H-\mu N)}] = \sum_{n_1, \dots, n_i, \dots} e^{-\beta \sum_i n_i (\epsilon_i - \mu)} = \prod_i \sum_{n_i = 0}^{\infty} [e^{-\beta(\epsilon_i - \mu)}]^{n_i} = \prod_i \frac{1}{1 - e^{-\beta(\epsilon_i - \mu)}}$$

So, the grand canonical potential of the system is

$$\Omega = -\beta^{-1} \ln Z_{\Omega} = T \sum_{i} \ln(1 - e^{-\beta(\epsilon_i - \mu)})$$

Note the chemical potential of the system must satisfy that

$$\mu < \epsilon_0$$

where ϵ_0 is the energy of the ground state.

To derive further results, we prefer to introduce a parameter z, defined by the relation

$$z \equiv e^{\beta\mu}$$

referred to as the fugacity of the system.

The expectation value of particle number is

$$N = - \left. \frac{\partial \Omega}{\partial \mu} \right|_{T,V} = \sum_i \frac{1}{e^{\beta \epsilon_i} z^{-1} - 1}$$

The expectation value of energy is

$$U = \sum_{i} \frac{\epsilon_i}{e^{\beta \epsilon_i} z^{-1} - 1}$$

The expectation value of particle number on level i is

$$n_i = \frac{1}{e^{\beta \epsilon_i} z^{-1} - 1}$$

3.1.2 Fermi-Dirac Statistics

If the system is composed of interaction-free Fermions, the state of the system can be denoted as

$$|n_1, n_2, \cdots, n_i, \cdots\rangle$$

where n_i is the number of particles in state $|i\rangle$ and $n_i=0$ or 1. Here, we choose $|i\rangle$ to the energy eigenstate with energy ϵ_i .

If we adopt grand-canonical ensemble, we have

$$Z_{\Omega} = \text{Tr}[e^{-\beta(H-\mu N)}] = \sum_{n_1, \dots, n_i, \dots} e^{-\beta \sum_i n_i (\epsilon_i - \mu)} = \prod_i \sum_{n_i = 0}^1 [e^{-\beta(\epsilon_i - \mu)}]^{n_i} = \prod_i 1 + e^{-\beta(\epsilon_i - \mu)}$$

So, the grand canonical potential of the system is

$$\Omega = -\beta^{-1} \ln Z_{\Omega} = -T \sum_{i} \ln(1 + e^{-\beta(\epsilon_i - \mu)})$$

The expectation value of particle number is

$$N = \sum_{i} \frac{1}{e^{\beta \epsilon_i} z^{-1} + 1}$$

The expectation value of energy is

$$U = \sum_{i} \frac{\epsilon_i}{e^{\beta \epsilon_i} z^{-1} + 1}$$

The expectation value of particle number on level i is

$$n_i = \frac{1}{e^{\beta \epsilon_i} z^{-1} + 1}$$

3.1.3 Boltzmann Statistics

If the system is composed of distinguishable interaction-free particles, the state of the system can be denoted as

$$|i_1, i_2, \cdots, i_N\rangle$$

where i_k is the state of k-th particle and N is the number of particle of the system. If we adopt canonical ensemble, we have

$$Z = \operatorname{Tr} e^{-\beta H} = \sum_{i, i} e^{-\beta \sum_{k=1}^{N} \epsilon_{i_k}} = \prod_{k=1}^{N} \sum_{i} e^{-\beta \epsilon_i}$$

Now, we define

$$Z_1 \equiv \sum_i e^{-\beta \epsilon_i}$$

we have

$$Z = (Z_1)^N$$



For a particle in a box, we can derive that $Z_1 \propto V \propto N$, so the free energy of the system is

$$F = -NT \ln Z_1 = -NT \ln N + \cdots$$

However, the term $-NT \ln N$ is not extensible. This is called Gibbs paradox. It is raised because our assumption that particles are distinguishable is wrong. This can be amended if we demand that

$$Z = \frac{Z_1^N}{N!}$$

then the non-extensible term is eliminated.

If we adopt the grand-canonical ensemble, we have

$$Z_{\Omega} = \sum_{N=0}^{\infty} \frac{z^{N} (Z_{1})^{N}}{N!} = \exp[Z_{1}z]$$

So, the grand canonical potential of the system is

$$\Omega = -\beta^{-1} \ln Z_{\Omega} = -T \sum_{i} e^{-\beta(\epsilon_{i} - \mu)}$$

The expectation value of particle number is

$$N = \sum_{i} \frac{1}{e^{\beta \epsilon_i} z^{-1}}$$

The expectation value of energy is

$$U = \sum_{i} \frac{\epsilon_i}{e^{\beta \epsilon_i} z^{-1}}$$

The expectation value of particle number on level i is

$$n_i = \frac{1}{e^{\beta \epsilon_i} z^{-1}}$$

As we can see, in the limit of

$$e^{\beta \epsilon_i} > e^{\beta \epsilon_0} \gg z$$

Bose-Einstein, Fermi-Dirac and Boltzmann statistics are identical.

3.2 Ideal Boltzmann Gas

3.2.1 Molecules without internal motion

Let us study thermodynamic properties of ideal gas. Our basic assumptions are:

- The temperature is high enough so that interaction between molecules can be neglected, i.e. $e^{-\frac{V}{T}} \ll 1$.
- Bose-Einstein or Fermi-Dirac statistics of the molecules can be well approximated by Boltzmann statistics, i.e. $z \ll 1$.



Suppose the side length of the box is L, the momentum of the particle must be the form of

$$\frac{2\pi}{L}(n_x, n_y, n_z)$$

where n_x , n_y and n_z are integers.

So we have

$$Z_1 = \sum_{n_x, n_y, n_z} e^{-\frac{\beta}{2m} (\frac{2\pi}{L})^2 (n_x^2 + n_y^2 + n_z^2)}$$

If the difference of adjacent energy level is much smaller than β^{-1} , i.e.

$$\frac{\beta}{2m}(\frac{2\pi}{L})^2 \ll 1$$

the summation can be approximately as an integral. In SI units, this condition can be written explicitly as

$$T \gg \frac{h^2}{2mk_B L^2} \sim 10^{-17} K$$

which is always satisfied in practice.

So we have

$$Z_1 = V \int \frac{d^3p}{(2\pi)^3} e^{-\frac{\beta p^2}{2m}} = \frac{V}{\lambda^3}$$

where $\lambda \equiv \frac{2\pi}{\sqrt{2\pi mT}}$



Note: When calculating the integral above, the following formula may by useful:

$$\int_0^\infty x^n e^{-ax^2} dx = \frac{\Gamma(\frac{n+1}{2})}{2a^{\frac{n+1}{2}}}$$

The free energy of the system is

$$F = -NT \ln(\frac{V}{\lambda^3}) + T \ln N! = -NT \ln(\frac{V}{N\lambda^3}) - NT$$

Calculation of other thermodynamic quantities is straightforward.

$$S = -\frac{\partial F}{\partial T}\Big|_{V,N} = N \ln \frac{V}{\lambda^3} + \frac{5}{2}N$$

$$U = F + TS = \frac{3}{2}NT$$

$$P = -\frac{\partial F}{\partial V}\Big|_{T,N} = \frac{NT}{V}$$

$$\mu = \frac{\partial F}{\partial N}\Big|_{T,V} = -T \ln \frac{V}{N\lambda^3}$$

$$C_V = \frac{\partial U}{\partial T}\Big|_{V,N} = \frac{3}{2}N$$

Note that

$$z = e^{\beta\mu} = \frac{N\lambda^3}{V}$$



We must have

$$\frac{\lambda^3}{v} \ll 1$$

to ensure that Boltzmann statistics is valid. In SI units, this condition can be written explicitly as

$$\frac{T^{3/2}}{\rho} \gg \frac{h^3}{(2\pi k_B)^{3/2} m^{5/2}} \sim O(1) \frac{\mathrm{K}^{3/2}}{\mathrm{kg/m}^3}$$

Usually, before this condition is violated, the interaction between molecules becomes important and the gas may transform to liquid already.

3.2.2 Molecules without internal motion

If the internal motion of molecules is taken into account, we have

$$Z_1 = \frac{V}{\lambda^3} j(T)$$

where

$$j(T) \equiv \sum_{i} g_{i} e^{-\beta \epsilon_{i}}$$

where ϵ_i is the energy associated with a state of internal motion, while g_i is the multiplicity of that state.

The contributions made by the internal motions of the molecules, over and above the translational degrees of freedom, follow straightforwardly from the function j(T). We obtain

$$F_{\text{int}} = -NT \ln j$$

$$\mu_{\text{int}} = -kT \ln j$$

$$S_{\text{int}} = N \left(\ln j + T \frac{\partial}{\partial T} \ln j \right)$$

$$U_{\text{int}} = NT^2 \frac{\partial}{\partial T} \ln j$$

$$(C_V)_{\text{int}} = N \frac{\partial}{\partial T} \left\{ T^2 \frac{\partial}{\partial T} \ln j \right\}$$

Thus, the central problem in this study is to derive an explicit expression for the function j(T) from a knowledge of the internal states of the molecules. For this, we note that the internal state of a molecule is determined by

- the electronic state
- the state of the nuclei
- the vibrational state
- the rotational state



Rigorously speaking, these four modes of excitation mutually interact; in many cases, however, they can be treated independently of one another. We can then write

$$j(T) = j_{\text{elec}}(T)j_{\text{nuc}}(T)j_{\text{vib}}(T)j_{\text{rot}}(T)$$

with the result that the net contribution made by the internal motions to the various thermodynamic properties of the system is given by a simple sum of the four respective contributions. A detailed discussion on gaseous systems composed of molecules with internal motion can be found in section 6.5 from *Statistical Mechanics* (*R.K.Pathria & Paul D.Beale*).

3.3 Ideal Bose Systems

Bose-Einstein condensation

For an ideal Bose gas, we have

$$\ln Z_{\Omega} = \frac{PV}{T} = -\sum_{i} \ln(1 - ze^{-\beta \epsilon_{i}})$$

and

$$N = \sum_{i} \frac{1}{z^{-1}e^{\beta\epsilon_i} - 1}$$

In view of the fact that, for large V, the spectrum of the single-particle states is almost a continuous one, the summations may be replaced by integrations.

We note that by replacing summation by integration we are inadvertently giving a weight zero to the energy level $\epsilon=0$. This is wrong because in a quantum mechanical treatment we must give a statistical weight unity to each non-degenerate single-particle state in the system. It is, therefore, advisable to take this particular state out of the sum in question before carrying out the integration; a rigorous justification of this unusual step can be found in Appendix F from Statistical Mechanics (R.K.Pathria & Paul D.Beale)

We thus obtain

$$\frac{P}{T} = -\frac{2\pi}{(2\pi)^3} (2m)^{3/2} \int_0^\infty \epsilon^{1/2} \ln(1 - ze^{-\beta \epsilon}) d\epsilon - \frac{1}{V} \ln(1 - z)$$

and

$$\frac{N}{V} = \frac{2\pi}{(2\pi)^3} (2m)^{3/2} \int_0^\infty \frac{\epsilon^{1/2} d\epsilon}{z^{-1} e^{\beta \epsilon} - 1} + \frac{1}{V} \frac{z}{1 - z}$$

For $z \ll 1$, which corresponds to situations not far removed from the classical limit, the last term of each equation is of order 1/N and, therefore, negligible.

However, as z increases and assumes values close to unity, the term $V^{-1}z/(1-z)$, which is identically equal to N_0/V (N_0 being the number of particles in the ground state), can well become a significant fraction of the quantity N/V; this accumulation of a macroscopic fraction of the particles into a single state leads to the phenomenon of Bose-Einstein condensation.

Nevertheless, since $z=N_0/(N_0+1)$, the term $-V^{-1}\ln(1-z)$ is equal to $V^{-1}\ln(N_0+1)$, which is at most $O(N^{-1}\ln(N+1))$; this term is, therefore, negligible for all values of z and



hence may be dropped altogether.

At last, we have

$$\frac{P}{T} = \frac{1}{\lambda^3} g_{5/2}(z)$$

and

$$\frac{N - N_0}{V} = \frac{1}{\lambda^3} g_{3/2}(z)$$

where $g_{\nu}(z)$ are Bose-Einstein functions defined by

$$g_{\nu}(z) \equiv \frac{1}{\Gamma(\nu)} \int_{0}^{\infty} \frac{x^{\nu-1} dx}{z^{-1} e^{x} - 1} = z + \frac{z^{2}}{2^{\nu}} + \cdots$$

The internal energy of this system is given by

$$U = -\left. \frac{\partial \ln Z_{\Omega}}{\partial \beta} \right|_{z,V} = \frac{3T}{2} \frac{V}{\lambda^3} g_{5/2}(z)$$

Thus, quite generally, our system satisfies the relationship

$$U = \frac{3}{2}PV$$

When the fugacity of the system is close to 1, we have

$$1 \ll N_0$$

and

$$\frac{N - N_0}{V} = \frac{1}{\lambda^3} \zeta(3/2)$$

where $\xi(\nu) = g_{\nu}(1)$. This curious phenomenon of a macroscopically large number of particles accumulating in a single quantum state is generally referred to as the phenomenon of Bose-Einstein condensation.

The condition for the onset of Bose-Einstein condensation is

$$T < T_c \equiv \frac{2\pi}{m} \left\{ \frac{N}{V\zeta(3/2)} \right\}^{2/3}$$

Here, T_c denotes a characteristic temperature that depends on the particle mass m and the particle density N/V in the system. Accordingly, for $T < T_c$, the system may be looked on as a mixture of two "phases":

- a normal phase, consisting of $N_e=N(T/T_c)^{3/2}$ particles distributed over the excited states
- a condensed phase, consisting of $N_0=N-N_e$ particles accumulated in the ground state



Pressure

Next, we examine the variation of P with T, keeping ν fixed. Now, for $T < T_c$, the pressure is given by

$$P = \frac{T}{\lambda^3} \zeta(5/2)$$

which is proportional to $T^{5/2}$ and is independent of v - implying infinite compressibility. At the transition point the value of the pressure is

$$P(T_c) = \frac{\zeta(5/2)}{\zeta(3/2)} \frac{NT_c}{V} \approx 0.5134 \frac{NT_c}{V}$$

Thus, the pressure exerted by the particles of an ideal Bose gas at the transition temperature is about one-half of that exerted by the particles of an equivalent Boltzmannian gas. For $T > T_c$, the pressure is given by

$$P = \frac{N}{V} T \frac{g_{5/2}(z)}{g_{3/2}(z)}$$

As $T \to \infty$, the pressure approaches the classical value.

Specific heat

For $T < T_c$, the specific heat is

$$\frac{C_V}{N} = \frac{3}{2} \frac{V}{N} \zeta(5/2) \frac{d}{dT} (\frac{T}{\lambda^3}) = \frac{15}{4} \zeta(5/2) \frac{v}{\lambda^3}$$

which is proportional to $T^{3/2}$. At $T=T_c$, we have $C_V(T_c)\approx 1.925N$, which is significantly higher than the classical value 1.5. For $T>T_c$, we obtain an implicit formula. First of all,

$$\frac{C_V}{N} = \left[\frac{\partial}{\partial T} \left(\frac{3}{2} T \frac{g_{5/2}(z)}{g_{3/2}(z)} \right) \right]_{ij}$$

Note the recurrence relation of Bose-Einstein function

$$z\frac{\partial g_{\nu}(z)}{\partial z} = g_{\nu-1}(z)$$

and recall that $g_{3/2}(z) = \lambda^3/v$, it is easy to get

$$\frac{1}{z} \left(\frac{\partial z}{\partial T} \right)_{v} = -\frac{3}{2T} \frac{g_{3/2}(z)}{g_{1/2}(z)}$$

At last, we have

$$\frac{C_V}{N} = \frac{15}{4} \frac{g_{5/2}(z)}{g_{3/2}(z)} - \frac{9}{4} \frac{g_{3/2}(z)}{g_{1/2}(z)}$$

In the limit $z \to 1$, the second term vanishes because of the divergence of $g_{1/2}(z)$, while the first term gives exactly the same result as in the case where $T \to T_c$ from below. The specific heat is, therefore, continuous at the transition point.

Its derivative is, however, discontinuous, the magnitude of the discontinuity being

$$\left. \frac{\partial C_V}{\partial T} \right|_{T=T_c-0} - \left. \frac{\partial C_V}{\partial T} \right|_{T=T_c+0} = \frac{27N}{16\pi T_c} \zeta(3/2)^2 \approx 3.665 \frac{N}{T_c}$$



Entropy

Finally, we examine the adiabats of the ideal Bose gas. For this, we need an expression for the entropy of the system. Making use of the thermodynamic formula $U-TS+PV=N\mu$, we get

$$s = \begin{cases} \frac{5}{2} \frac{g_{5/2}(z)}{g_{3/2}(z)} - \ln z & T > T_c \\ \frac{5}{2} \frac{v}{\lambda^3} \zeta(5/2) & T < T_c \end{cases}$$

Now, a reversible adiabatic process implies the constancy of s. For $T > T_c$, this implies the constancy of z as well and in turn the constancy of $v/lambda^3$. For $T \leq T_c$, it again implies the same. We thus obtain, quite generally, the following relationship between the volume and the temperature of the system when it undergoes a reversible adiabatic process:

$$vT^{3/2} = \text{const.}$$

The corresponding relationship between the pressure and the temperature is

$$P/T^{5/2} = \text{const.}$$

Eliminating T, we obtain

$$Pv^{5/3} = \text{const.}$$

as the equation for an adiabat of the ideal Bose gas.



Note: Incidentally, the foregoing results are exactly the same as for an ideal classical gas. There is, however, a significant difference between the two cases; that is, while the exponent 5/3 is identically equal to the ratio of the specific heats C_P and C_V in the case of the ideal classical gas, it is not so in the case of the ideal Bose gas.

In the mixed-phase region, the entropy of the gas may be written as

$$S = N_e \frac{5}{2} \frac{\zeta(5/2)}{\zeta(3/2)}$$

As expected, the N_0 particles that constitute the condensate do not contribute toward the entropy of the system, while the N_e particles that constitute the normal part contribute an amount of $\frac{5}{2} \frac{\zeta(5/2)}{\zeta(3/2)}$ per particle.

3.4 Ideal Fermi systems

General properties of ideal Fermi systems

For an ideal Fermi gas, we have

$$\frac{PV}{T} = \ln Z_{\Omega} = \sum_{i} \ln(1 + ze^{-\beta\epsilon_{i}})$$

and

$$N = \sum_{i} \frac{1}{e^{\beta \epsilon_i} z^{-1} + 1}$$



Unlike the Bose case, the parameter z in the Fermi case can take on unrestricted values. Moreover, in view of the Pauli exclusion principle, the question of a large number of particles occupying a single energy state does not even arise in this case. We can replace summations by corresponding integrations. We thus obtain

$$\frac{P}{T} = \frac{g}{\lambda^3} f_{5/2}(z)$$

and

$$\frac{N}{V} = \frac{g}{\lambda^3} f_{3/2}(z)$$

where g is a weight factor arising from the internal structure of the particles and $f_{\nu}(z)$ are Fermi-Dirac functions defined by

$$f_{\nu}(z) \equiv \frac{1}{\Gamma(\nu)} \int_{0}^{\infty} \frac{x^{\nu-1} dx}{z^{-1} e^{x} + 1} = z - \frac{z^{2}}{2^{\nu}} + \frac{z^{3}}{3^{\nu}} - \cdots$$

The internal energy of the Fermi gas is given by

$$U = -\left. \frac{\partial \ln Z_{\Omega}}{\partial \beta} \right|_{z,V} = \frac{3T}{2} \frac{gV}{\lambda^3} f_{5/2}(z)$$

thus, quite generally, this system satisfies the relationship

$$U = \frac{3}{2}PV$$

Similarly, note the recurrence relation of Fermi-Dirac function

$$z\frac{\partial f_{\nu}(z)}{\partial z} = f_{\nu-1}(z)$$

it is easy to get the specific heat of the gas:

$$\frac{C_V}{N} = \frac{15}{4} \frac{f_{5/2}(z)}{f_{3/2}(z)} - \frac{9}{4} \frac{f_{3/2}(z)}{f_{1/2}(z)}$$

For the Helmholtz free energy of the gas, we get

$$F = N\mu - PV = NT \left\{ \ln z - \frac{f_{5/2}(z)}{f_{3/2}(z)} \right\}$$

and for the entropy

$$S = \frac{U - F}{T} = N \left\{ \frac{5}{2} \frac{f_{5/2}(z)}{f_{3/2}(z)} - \ln z \right\}$$

In order to determine the various properties of the Fermi gas in terms of the particle density n and the temperature T, we need to know the functional dependence of the parameter z on n and T; this information is formally contained in the implicit relationship $gf_{3/2}(z)=n\lambda^3$. Now, if the density of the gas is very low and/or its temperature very high, then the situation might correspond to $f_{3/2}(z)\ll 1$; we then speak of the gas as being non-degenerate and, therefore, equivalent to a classical ideal gas.



If the parameter z is small in comparison with unity but not very small, then we should obtain an expansion for z in powers of $n\lambda^3/g$ and then substitute this expansion into the

$$\frac{PV}{NT} = \frac{f_{5/2}(z)}{f_{3/2}(z)}$$

If the density and the temperature are such that the parameter $(n\lambda^3/g)$ is of order unity, the foregoing expansions cannot be of much use. In that case, one may have to make recourse to numerical calculation.

If $(n\lambda^3/g) \gg 1$, the functions involved can be expressed as asymptotic expansions in powers of $(\ln z)^{-1}$; we then speak of the gas as being degenerate.

As $(n\lambda^3/g) \to \infty$, our functions assume a closed form, with the result that the expressions for the various thermodynamic quantities pertaining to the system become highly simplified; we then speak of the gas as being completely degenerate.

Completely degenerate case

In the limit $T \to 0$, which implies $(n\lambda^3/g) \to \infty$, the mean occupation numbers of the single-particle state become

$$\langle n_i \rangle = \frac{1}{e^{\beta(\epsilon_i - \mu)} + 1} = \begin{cases} 1 \text{ for } \epsilon_i < \mu_0 \\ 0 \text{ for } \epsilon_i > \mu_0 \end{cases}$$

where μ_0 is the chemical potential of the system at T=0.

Thus, at T=0, all single-particle states up to μ_0 are "completely" filled, with one particle per state, while all single-particle states with $\epsilon_i>\mu_0$ are empty. The limiting energy μ_0 is generally referred to as the Fermi energy of the system and is denoted by the symbol ϵ_F ; the corresponding value of the single-particle momentum is referred to as the Fermi momentum and is denoted by the symbol p_F . The defining equation for these parameters is

$$\int_0^{\epsilon_F} = a(\epsilon)d\epsilon$$

where $a(\epsilon)$ denotes the density of states of the system and is given by the general expression

$$a(\epsilon) = \frac{gV}{(2\pi)^3} 4\pi p^2 \frac{dp}{d\epsilon}$$

We readily obtain

$$N = \frac{gV}{6\pi^2} p_F^3$$

which gives

$$p_F = \left(\frac{6\pi^2 N}{gV}\right)^{1/3} \quad \epsilon_F = \frac{1}{2m} \left(\frac{6\pi^2 n}{g}\right)^{2/3}$$

The ground-state, or zero-point, energy of the system is then given by

$$U_0 = \frac{4\pi gV}{(2\pi)^3} \int_0^{p_F} \frac{p^2}{2m} p^2 dp = \frac{gV p_F^5}{20\pi^2 m} = \frac{3}{5} N \epsilon_F$$

The ground-state pressure of the system is in turn given by

$$P_0 = \frac{2U_0}{3V} = \frac{2}{5}n\epsilon_F \propto n^{5/3}$$



Degenerate case

For an analytical study of the Fermi gas at finite, but low, temperatures, we observe that the value of z, which was infinitely large at absolute zero, is now finite, though still large in comparison with unity. The functions $f_{\nu}(z)$ can, therefore, be expressed as asymptotic expansions in powers of $(\ln z)^{-1}$. For the values of ν we are presently interested in, we have to the first approximation

$$f_{5/2}(z) = \frac{8}{15\pi^{1/2}} (\ln z)^{5/2} \left[1 + \frac{5\pi^2}{8} (\ln z)^{-2} + \cdots \right]$$

$$f_{3/2}(z) = \frac{4}{3\pi^{1/2}} (\ln z)^{3/2} \left[1 + \frac{\pi^2}{8} (\ln z)^{-2} + \cdots \right]$$

$$f_{1/2}(z) = \frac{2}{\pi^{1/2}} (\ln z)^{1/2} \left[1 - \frac{\pi^2}{24} (\ln z)^{-2} + \cdots \right]$$

Thus, we obtain

$$\frac{N}{V} = \frac{g(2m)^{3/2}}{6\pi^2} (T \ln z)^{3/2} \left[1 + \frac{\pi^2}{8} (\ln z)^{-2} + \cdots \right]$$

In the first order approximation, we obtain

$$\mu = T \ln z \approx \epsilon_F \left[1 - \frac{\pi^2}{12} \left(\frac{T}{\epsilon_F} \right)^2 \right]$$

So, we have

$$\frac{U}{N} = \frac{3}{5} (\ln zT) \left[1 + \frac{\pi^2}{2} (\ln z)^{-2} + \dots \right] = \frac{3}{5} \epsilon_F \left[1 + \frac{5\pi^2}{12} \left(\frac{T}{\epsilon_F} \right)^2 + \dots \right]$$

The pressure of the gas is then given by

$$P = \frac{2U}{3V} = \frac{2}{5}n\epsilon_F \left[1 + \frac{5\pi^2}{12} \left(\frac{T}{\epsilon_F} \right)^2 + \cdots \right]$$

For the low temperature specific heat of the gas is

$$\frac{C_V}{N} = \frac{\pi^2}{2} \frac{T}{\epsilon_F} + \cdots$$

The Helmholtz free energy of the system is

$$\frac{F}{N} = \mu - \frac{PV}{N} = \frac{3}{5}\epsilon_F \left[1 - \frac{5\pi^2}{12} \left(\frac{T}{\epsilon_F} \right)^2 + \cdots \right]$$

which gives

$$\frac{S}{N} = \frac{\pi^2}{2} \frac{T}{\epsilon_E} + \cdots$$

Thus, as $T \to 0$, $S \to 0$ in accordance with the third law of thermodynamics.



3.5 Thermodynamics of the blackbody radiation

We consider a radiation cavity of volume V at temperature T. The system can be looked as a gas of identical and indistinguishable quanta - the so-called photons. Because the number of photons is not conserved, the chemical potential of photon gas in equilibrium must be zero. Since zero chemical potential means that the ensemble is not allowed to punish states with different values of N. So, we have

$$\langle n_i \rangle = \frac{1}{e^{\beta \epsilon_i} - 1}$$

The internal energy of the system is

$$U = \sum_{i} \frac{\epsilon_i}{e^{\beta \epsilon_i} - 1}$$

The summation can be approximated by an integral. Note the spin of a photon can take two distinct values, we have

$$U = \frac{VT^4}{\pi^2} \int_0^\infty \frac{x^3 dx}{e^x - 1} = \frac{VT^4}{\pi^2} \Gamma(4) \zeta(4) = \frac{\pi^2 VT^4}{15}$$

If there is a small opening in the walls of the cavity, the photons will "effuse" through it. The net rate of flow of the radiation, per unit area of the opening, will be

$$I = \frac{1}{2} \int \frac{U}{V} \cos^2 \theta d\theta = \frac{U}{4V} = \frac{\pi^2}{60} T^4$$

It is the so-called Stefan-Boltzmann law of blackbody radiation.

For further study of thermodynamics, we evaluate the grand partition function of the photon gas:

$$\frac{PV}{T} = -\frac{VT^3}{\pi^2} \int_0^\infty \ln(1 - e^{-x}) x^2 dx = \frac{VT^3}{3\pi^2} \int_0^\infty \frac{x^3 dx}{e^x - 1}$$

So, we have

$$PV = \frac{1}{3}U$$

Next, since the chemical potential of the system is zero, the Helmholtz free energy is equal to -PV; therefore the entropy is given by

$$S = \frac{U - F}{T} = \frac{4U}{3T} \propto VT^3$$

and

$$C_V = T \left. \frac{\partial S}{\partial T} \right|_T = 3S$$

Finally, we derive an expression for the equilibrium number N of photons in the radiation cavity. We obtain

$$N = V \frac{2\xi(3)T^3}{\pi^2} \propto VT^3$$

Instructive though it may be, formula above cannot be taken at its face value because in the present problem the magnitude of the fluctuations in the variable N, which is determined by the quantity $\left(\frac{\partial P}{\partial V}\right)^{-1}$, is infinitely large.

