



PUBLIC

SAP Signavio

2026-04-15

Business Process Model Connector for SAP Signavio Solutions

Content

1	Business Process Model Connector for SAP Signavio Solutions.	4
2	Log in with business process model connector for SAP Signavio solutions.	7
3	Getting Started.	9
3.1	Cloud Connector.	9
	Installing the Cloud Connector.	9
	Connecting the Cloud Connector to Your Subaccount.	10
3.2	Business process model connector for SAP Signavio solution.	11
	Entitlements and Subaccounts Needed for Subscribing to the Connector.	11
	Subscribing to the Connector Application.	12
	Launching the Connector Application.	13
	Logging out of the Connector Application.	14
4	Synchronization Objects and Functionality.	16
4.1	Synchronization of Folders.	17
4.2	Synchronization of Processes.	19
4.3	Import of BPMN Diagram from SAP Solution Manager.	21
4.4	Importing Models to SAP Solution Manager.	22
4.5	Synchronization of Variant Management.	24
4.6	Synchronization of Process Steps.	25
4.7	Synchronization of Linked Diagrams to SAP Solution Manager.	26
4.8	Synchronization of Dictionary (Activity) and Process Step Library.	29
4.9	Synchronization of Executables.	30
4.10	Synchronization of Attributes.	38
4.11	Supported Languages.	39
4.12	Deletion of Synchronized Objects.	40
4.13	SAP Solution Manager Scope in Synchronization.	41
5	Connect.	42
5.1	Connecting Signavio Process Manager.	43
	Editing Connected System - SAP Signavio.	45
5.2	Connecting SAP Solution Manager.	46
	Editing Connected System - SAP Solution Manager.	50
	Necessary User Rights.	51
5.3	Creating the Trust Relationship.	52
6	Configure.	54

6.1	Creating a Synchronization Project.	54
	Synchronization Test Scenarios.	55
6.2	Editing a Synchronization Project.	56
	Pin Synchronization Projects for Later Editing.	57
6.3	Mapping Objects.	58
6.4	Mapping Attributes and Setting the Deletion Flag.	60
	Adding a Deletion Flag During an Active Synchronization Project.	62
	Deletion Flag Functionality.	63
	Reverted Deleted Tasks.	64
6.5	Previewing and Activating a Synchronization Project.	64
7	Run.	66
7.1	Activating a Synchronization Project.	66
7.2	Running a Synchronization.	67
8	System Settings.	70
9	Monitor.	71
9.1	Synchronization History.	71
10	Security Guide.	73
10.1	Creating Users.	73
10.2	Assigning Roles.	74
10.3	Audit Logs.	76
10.4	Setting the Synchronization Log Retention Period.	78
10.5	Data Security.	80
10.6	Advanced IP-Based Security.	81
11	Troubleshooting.	84
11.1	Troubleshooting - Creating a Subaccount.	87
11.2	Creating a Support Case.	88
11.3	Built-In Support.	89

1 Business Process Model Connector for SAP Signavio Solutions

The connector application allows you to consistently synchronize data between SAP Solution Manager and SAP Signavio Process Manager.


The New Connector and Migration from the Classic Connector

Built on SAP Business Technology Platform (SAP BTP) as a standalone cloud application, the newest version of the connector is known as the **business process model connector for SAP Signavio solutions**. This version leverages SAP BTP services to enable the connectivity of multiple SAP Signavio Process Manager and SAP Solution Manager systems at once.

The business process model connector for SAP Signavio solutions replaces the classic connector.

Note

Mainstream maintenance for the classic connector remains available until the end of **March 2026**. There is no extended maintenance planned. If you currently use the classic connector, we recommend migrating your synchronization data with the business process model connector for SAP Signavio solutions before the mainstream maintenance period ends.



To migrate your synchronized data from the classic connector using the business process model connector for SAP Signavio solutions, see SAP Note [3656181](#). Once the migration is complete and accepted, access to the classic connector is restricted. You can make future synchronization updates between SAP Solution Manager and SAP Signavio Process Manager with the business process model connector for SAP Signavio solutions.

If you need technical support with data migration, create a support ticket with [SAP Signavio Support](#) and reference component BPI-SIG-CA-BMB.

The New Connector and Migration of SAP Solution Manager 7.2 to SAP Cloud ALM

The new connector, known as business process model connector for SAP Signavio solutions follows the maintenance approach of SAP Solution Manager 7.2, as described in [Maintenance Information](#).

Note

If you plan to migrate from SAP Solution Manager to SAP Cloud ALM, we recommend that you migrate from the classic connector to using the business process model connector for SAP Signavio solutions by the end of **March 2026**.

There is no migration path provided for the classic connector to migrate your synchronized data to SAP Signavio Process Manager and SAP Cloud ALM integration.

Using the business process model connector for SAP Signavio solutions for your SAP Signavio Process Manager and SAP Solution Manager integration results in continuous and consistent synchronization between SAP Signavio Process Manager and SAP Cloud ALM after migration from SAP Solution Manager to SAP Cloud ALM. For more information, see [Selective data transfer from SAP Solution Manager to SAP Cloud ALM](#).

Prerequisites for Using the New Connector

If you are a current user of the classic connector, you migrated your synchronized data using the new connector, as described in SAP Note [3656181](#).

Caution

To prevent data duplication and inconsistent data transfer, ensure that you use only the new connector for future synchronizations.

If you aren't currently using the classic connector, you set up the new connector application, as described in [Subscribing to the Connector Application](#).

For initial synchronization with the business process model connector for SAP Signavio solutions, you emptied either your SAP Solution Manager *process step library* folder or your SAP Signavio *dictionary category (activity)*, depending on the target system for synchronization.

Synchronization Direction: SAP Signavio Process Manager --> SAP Solution Manager

For SAP Signavio Process Manager to SAP Solution Manager synchronization, the following conditions must be met:

- The source root folder must contain all processes required to be synchronized. The source root folder can be *Shared Folders* or its level-1 sub-folder.
- All tasks used in process models that need to be synchronized must exist in the SAP Signavio Process Manager dictionary as activities.
- The SAP Solution Manager folder *Business Process* can contain level-1 sub-folders or be empty. Either the *Business Process* folder or its level-1 sub-folder can be selected as a root folder to store imported objects.
- The SAP Solution Manager process step library folder must be empty.

Synchronization Direction: SAP Solution Manager --> SAP Signavio Process Manager

For SAP Solution Manager to SAP Signavio Process Manager synchronization, the following conditions must be met:

- The source root folder must contain all processes required to be synchronized. The source root folder can be *Business Process* or one of its level-1 sub-folders.

- The SAP Signavio Process Manager folder [Shared Documents](#) must be empty or contain at least one level-1 empty sub-folder that can be used as a target root folder. This is where the process structure of SAP Solution Manager is imported.
- Target SAP Signavio [dictionary category \(activity\)](#) must be empty.

Synchronization Activities

The connector currently supports synchronization of the following objects:

- Folders and scenarios
- Process models
- Linked models (to SAP Solution Manager)
- Variant Management and Dimension (to SAP Solution Manager)
- Process steps used in process models
- Process steps stored in the following:
 - Library of SAP Solution Manager
 - Dictionary of SAP Signavio Process Manager
- Standard and custom attributes (for limited data element types). See [Synchronization of Attributes \[page 38\]](#).
- BPMN diagrams import (to SAP Signavio Process Manager)

Post Initial Synchronization

After an initial synchronization, SAP Signavio Process Manager becomes the **leading system** for managing changes to these objects and their mapped attribute values. The objects listed above can only be updated in SAP Signavio Process Manager. Updates can then be transferred to SAP Solution Manager by using the business process model connector for SAP Signavio solutions to synchronize the changed objects.

2 Log in with business process model connector for SAP Signavio solutions

Browser Compatibility

SAP Signavio supports all popular browsers. For a detailed description of the supported browsers, see [Browser Compatibility](#).

Log In With Your Account Credentials

After you've created your SAP Signavio Process Transformation Suite account (see [Signing Up](#)), use your account e-mail and password to log in.

In the case that your workspace administrator has created the account for you, you received an e-mail to reset your password. When SSO is enabled for your workspace, you log in using a shared link.

1. Go to the login page:
 - <https://app-au.signavio.com> (region: Australia)
 - <https://app-ca.signavio.com> (region: Canada)
 - <https://editor.signavio.com> (region: Europe)
 - <https://app-jp.signavio.com> (region: Japan)
 - <https://app-kr.signavio.com> (region: Korea)
 - <https://app-sgp.signavio.com> (region: Singapore)
 - <https://app-us.signavio.com> (region: US)
2. Enter your account e-mail and password and click [Login](#).
If you receive the error message that the login with e-mail and password is disabled, SSO is enforced for your workspace and you need to log in using a shared link.
3. Select your workspace and choose [Login](#). SAP Signavio Process Collaboration Hub launchpad opens.
4. In the top navigation bar, choose the SAP Signavio product that you need, using the  app switcher.

Log In Using a Shared Link

When SSO is enabled for your workspace, you log in through a shared link. The link is shared with you, for example, in an invitation e-mail or on a wiki page.

Note

We recommend that you bookmark the shared link for future logins. Depending on your workspace configuration, you might only be able to log in to SAP Signavio Process Transformation Suite through the shared link.

1. Select the link.
2. Follow the steps that you see on the screen. Your account is authenticated by a third-party application.
3. After successful login, the SAP Signavio Process Collaboration Hub launchpad opens.
4. In the top navigation bar, choose the SAP Signavio product that you need, using the  app switcher.

3 Getting Started

This section introduces the recommended workflow when using the connector and describes initial setup.

The workflow includes several steps. Each step of the workflow is described in a section of this guide:

1. [Subscribe](#) to the connector application, which enables users to log into the connector.
2. [Connect](#) SAP Signavio Process Manager and SAP Solution Manager systems.
3. [Configure](#) the synchronization of data between systems.
4. [Run](#) synchronizations to transfer data between systems.
5. [Monitor](#) the progress and performance of synchronizations.

3.1 Cloud Connector

3.1.1 Installing the Cloud Connector

Use the Cloud Connector to secure connectivity from SAP Business Technology Platform (SAP BTP) to SAP Solution Manager.

Prerequisites

You downloaded the Cloud Connector from [SAP Development Tools](#).

Context

The Cloud Connector is required to secure connectivity from SAP BTP to SAP Solution Manager. You need to install the Cloud Connector on a virtual machine at the customer data center.

Procedure

1. Create a virtual machine. To do so, follow the sizing guidelines from the SAP BTP Connectivity guide. **We recommend using medium size as a minimum.**
2. Install the Cloud Connector on the virtual machine. To do so, follow the installation instructions from the SAP BTP Connectivity guide for your chosen operating system (Windows, Linux, or Mac).

Installation is complete and you can proceed with post-installation finalization actions.

3. Configure the Cloud Connector for HTTP. To do so, follow the initial configuration guidelines from the SAP BTP Connectivity guide.
4. Apply the SAP BTP Connectivity guide's recommended guidelines for a secure setup.

Related Information

[Virtual Machine Sizing Guidelines - SAP BTP Connectivity](#)

[Cloud Connector Installation - SAP BTP Connectivity](#)

[Cloud Connector Initial Configuration \(HTTP\) - SAP BTP Connectivity](#)

[Cloud Connector Recommendation for Secure Setup - SAP BTP Connectivity](#)

3.1.2 Connecting the Cloud Connector to Your Subaccount

Learn how to connect the Cloud Connector to a subaccount.

Procedure

1. Follow the steps from SAP Business Technology Platform (SAP BTP) Connectivity guide for adding and connecting a subaccount.
 - Select your region.
 - (Mandatory - must not be blank) Provide a location ID, for example, the customer name or an abbreviation. This allows for using the Cloud Connector for connectivity to on-premise systems from other subaccounts for other applications.

⚠ Caution

While the Cloud Connector supports the underscore character (_) as a location ID, underscore is not supported by the business process model connector for SAP Signavio solutions. As a result, the connector cannot create a virtual hostname for a destination SAP Solution Manager system when the location ID includes an underscore.

- Use the email address associated with your SAP Logon-ID for SAP Support Services (such as Support Launchpad) for your user.

📌 Note

This email should not be used for an SAP Universal ID since it is not supported by the Cloud Connector.

- Your password is the same password for your SAP Logon-ID.
2. Once connected, verify the connection with the Cloud Connector.
 - a. From the SAP BTP Cockpit, choose ► [Connectivity](#) ► [Cloud Connectors](#) ►.

Your connection is marked as active.

For additional details on connecting subaccounts to the Cloud Connector, to include test subaccounts, see [Managing Subaccounts](#).

3.2 Business process model connector for SAP Signavio solution

3.2.1 Entitlements and Subaccounts Needed for Subscribing to the Connector

Before you can subscribe to the business process model connector for SAP Signavio solutions, your SAP Business Technology Platform (SAP BTP) administrator must create a subaccount in an available region.

You can find the business process model connector for SAP Signavio solutions in your global account under [► Entitlements ► Service Assignments ►](#).

The business process model connector for SAP Signavio solutions is currently available in these regions:

- EU10 (AWS – Frankfurt)
- US10 (AWS – Virginia)

Once the subaccount has been created, your SAP BTP administrator must assign the business process model connector for SAP Signavio solutions to the subaccount's entitlements. For more information, see [Preparing Entitlements and Subaccounts Needed for Subscribing to the Connector \[page 11\]](#).

3.2.1.1 Preparing Entitlements and Subaccounts Needed for Subscribing to the Connector

Learn how you, an SAP Business Technology Platform (SAP BTP) administrator, can assign the business process model connector for SAP Signavio solutions to a subaccount's entitlements.


Prerequisites

You have SAP BTP administrator rights.

Procedure

1. In your global account, navigate to the menu option [► Entitlements ► Entity Assignments ►](#).

2. Choose [Select Entities](#) and select the relevant subaccount.
3. Choose [Configure Entitlements](#).
4. Choose [Add Service Plans](#) and search for the business process model connector for SAP Signavio solutions in the search field.
5. Select business process model connector for SAP Signavio solutions from the results.
6. Select the [free \(Application\)](#) option and choose [Add 1 Service Plan](#).



7. Save your entries.

3.2.2 Subscribing to the Connector Application

Learn how you, an SAP Business Technology Platform (SAP BTP) administrator, can enable users to log onto the business process model connector for SAP Signavio solutions.

Prerequisites

- You have SAP BTP administrator rights.
- You have created the subaccount in the supported region.
- You have added the entitlement for the business process model connector for SAP Signavio solutions to your subaccount.

Context

To enable users to log into the business process model connector for SAP Signavio solutions, the business process model connector for SAP Signavio solutions must be deployed to use the subaccount.

Procedure

1. From the SAP BTP Cockpit, select [Service Marketplace](#).
2. Find the tile [business process model connector for SAP Signavio solutions](#).
3. Choose  ([more options](#)) and select [Create](#).

This starts the subscription process.

4. After the process is complete, choose .
5. Select your user and add the required [FullAdmin](#) role.

For more information about roles, see [Assigning Roles \[page 74\]](#).

Results

The application is deployed to use the subaccount. You are ready to log into the business process model connector for SAP Signavio solutions and launch the connector application.

Related Information

[Launching the Connector Application \[page 13\]](#)

3.2.3 Launching the Connector Application

Learn how to begin using the business process model connector for SAP Signavio solutions.

Prerequisites

- You, as an end user, installed and connected the Cloud Connector.
- Your SAP Business Technology Platform (SAP BTP) administrator followed instructions in [Preparing Entitlements and Subaccounts Needed for Subscribing to the Connector \[page 11\]](#) and [Subscribing to the Connector Application \[page 12\]](#).

Procedure

1. From the SAP BTP Cockpit at subaccount level, choose ► [Services](#) ► [Instances and Subscriptions](#) ►.
2. Under [Subscriptions](#), choose business process model connector for SAP Signavio solutions.
3. Choose [Go to Application](#).

Results

The business process model connector for SAP Signavio solutions opens to the main menu of the application.

3.2.4 Logging out of the Connector Application

Learn how to properly log out of the business process model connector for SAP Signavio solutions at the end of your session.

Context

Closing a business process model connector for SAP Signavio solutions window does not end your session. If you open a new window and navigate to the business process model connector for SAP Signavio solutions home page again, you see that you are already logged in and that there is no login instruction displayed.


Procedure

1. From your current system window, select  ([User Profile Menu](#)).

Note

[User Profile Menu](#) displays your own initials as the logged in user.

Alternatively, from the home page, choose the tile [Connected systems](#).



2. Sign out.
3. Confirm and close the window.

Note

When you open a new window and navigate to the business process model connector for SAP Signavio solutions home page, you see login instruction displayed.

4 Synchronization Objects and Functionality

Learn how specific object types are supported in synchronization.

Scope of Objects

The following object types are supported in synchronization:

- Folders and scenarios
- Process models
- Process steps used in process models
- Process steps stored in the following:
 - Library of SAP Solution Manager
 - Dictionary of SAP Signavio Process Manager
- Executables
- Standard and custom attributes (for limited data element types).
See [Synchronization of Attributes \[page 38\]](#).
- Linked diagrams (to SAP Solution Manager).
See [Synchronization of Linked Diagrams to SAP Solution Manager \[page 26\]](#).
- BPMN Diagrams Import (to SAP Signavio Process Manager)

Synchronized object types are mapped as follows between SAP Signavio Process Manager and SAP Solution Manager:

SAP Signavio Object Types	SAP Solution Manager Object Types
Root folder	Root folder
Folder	Folder
Folder	Scenario
BPMN Diagram 2.0	Process
Linked diagram	Process Link
Task	Process Step <Ref.>
Activity (Dictionary)	Process Step <Orig.>
Dictionary (Others) object	Executable <Orig.>
Dictionary Link (list) of Task and/or Activity	Executable <Ref.>
Dictionary Category (Activity)	Process Step Library

The connector maps and synchronizes the IDs of the above-mentioned objects and not the objects' names. If objects have the same names but different IDs, then both objects with identical names are synchronized and visible in the target system.

Process Structure Objects

Note

Synchronization of process structure objects from SAP Solution Manager to SAP Signavio must be used for initial import of process content only. Update synchronization from SAP Solution Manager to SAP Signavio is not supported and results in an error.

For more information about synchronization best practices and various approaches that might be applied, see [Integration of SAP Signavio Process Manager with SAP Solution Manager 7.2](#).

Executable Objects

Synchronization of *Executable <Orig.>* objects requires an import from SAP Solution Manager to SAP Signavio. Changes to *Executable <Orig.>* objects must be made in SAP Solution Manager, then sent to SAP Signavio, using SAP Solution Manager to SAP Signavio synchronization.

Synchronization of *Executable <Ref.>* objects from SAP Solution Manager to SAP Signavio must be used for initial import only.

Note

If the initial import needs to be repeated, then all previously imported *Executable <Ref.>* objects will be overwritten apart from local changes that took place directly in SAP Signavio after the previous (initial) import.

After the successful initial import of *Executable <Ref.>* objects as assignments to *Activity* or *Task*, changes of assigned *Executable <Ref.>* objects must take place in SAP Signavio only.

4.1 Synchronization of Folders

Learn more about synchronization requirements for folder and scenarios, which vary depending on the direction of synchronization.

Root Folders

The default SAP Signavio top root folder called *Shared Documents* can be mapped to SAP Solution Manager root folder called *Business Processes*. Any level 1 folder can be used as a top root folder in the source and target systems. This enables selection of the specific content from the default top root folder to be included in synchronization from the source system. It also allows you to define a custom top root folder that will be used to receive the content in the target system.

Synchronization direction: SAP Signavio --> SAP Solution Manager

All sub-folders from SAP Signavio's top root folder will be included and created under the top root folder of SAP Solution Manager, such as directly under *Business Processes* or a custom level 1 folder.

If SAP Signavio top root folder contains any object other than a folder, the object is ignored during the synchronization run. A warning message for each ignored object is added to the synchronization log. The warning message also advises to move the object to the required lower level folder and execute another synchronization run.

Synchronization direction: SAP Solution Manager --> SAP Signavio

All sub-folders from SAP Solution Manager's top root folder will be included and created under the top root folder of SAP Signavio, such as directly under *Shared Documents* or a custom level 1 folder. If SAP Solution Manager's scope is used during the synchronization run, then the process content of the selected scope will be imported to SAP Signavio, as a hierarchy of sub-folders under the specified top root folder.

In the source system, the selected top root folder may only contain other folders in SAP Signavio or folders and scenarios in SAP Solution Manager. The top folder of SAP Signavio may not contain models, for example.

The selected top root folder must be empty in the target system.

The top root folder must not be changed or renamed in SAP Signavio or SAP Solution Manager if it is used at least in one synchronization run.

Folders and Scenarios

Depending on synchronization directions, the following functionality and actions are supported.

Synchronization direction: SAP Signavio --> SAP Solution Manager

Folders can contain a hierarchy of other folders representing the process structure. The folders that contain BPMN Diagram 2.0 objects will be synchronized to SAP Solution Manager as scenarios.

Note

Folders that contain BPMN Diagram 2.0 objects must not contain sub-folders. Folders that contain sub-folders must not contain diagrams.

All folders that are not empty under the top root folder can be synchronized to SAP Solution Manager.

Empty folders, containing no other folders or models, will not be included in synchronization as it's not possible to establish if the folder needs to be transferred to SAP Solution Manager as a folder or a scenario (depending on the object type that will be added to it during modeling activities in SAP Signavio).

Synchronization direction: SAP Solution Manager --> SAP Signavio

SAP Solution Manager structure can contain a hierarchy of folders and scenarios. All folders and scenarios under the top root folder can be synchronized to SAP Signavio.

Empty folders are synchronized to SAP Signavio also as folder object type. Those folders in SAP Signavio must be used to add other sub-folders and stay aligned with SAP Solution Manager folders. If a BPMN Diagram 2.0 object type is added to the empty folder, the model will be ignored in synchronization, because the empty folder is not mapped to the scenario object type.

After initial synchronization, folders and scenarios synchronized to SAP Signavio at least once, must not be changed in SAP Solution Manager. The objects must be changed only in SAP Signavio, which is the leading tool

for managing process structure (hierarchy) changes. The objects are synchronized via the follow-up update synchronization run to SAP Solution Manager. Only associated elements and attributes (such as assigned documents, executables, and attributes that are not in scope of synchronization) can be still changed in SAP Solution Manager.

📌 Note

Error message can be displayed when running sync: "Sync errored for ObjectType: FOLDER with error: Map internal to external failed for direction: SPM2SOLUTION MANAGER with error: Error: Solution Manager FolderObject: [Object ID] cannot be converted to 'SCN - Scenario' with name and ID".

Adjust SAP Signavio process Folder object and repeat synchronization.

Empty scenarios are synchronized to SAP Signavio as folder object type. BPMN Diagram 2.0 object types only must be added to this folder that is mapped in SAP Solution Manager as a scenario. All other objects will be ignored in synchronization.

📌 Note

An error message will be displayed: Sync errored for ObjectType: FOLDER with error: OBJ_TYPE DOES NOT MATCH FOR:4j97UdxW7ksoYNivBJrC{0. with name and ID.

Adjust SAP Signavio process folder or scenario object and repeat synchronization.

📌 Note

Folder and scenario objects that were synchronized at least once, must not be deleted in SAP Signavio or SAP Solution Manager. If the object is no longer required, consider creating a new folder called [Archived Folders /Scenarios](#) and move the object into this folder. The object name might need to be changed with the prefix [Deleted](#) if required.

If folder or scenario objects are deleted, synchronization will be inconsistent.

4.2 Synchronization of Processes

Learn details of synchronization in SAP Solution Manager and SAP Signavio.

Synchronization of Processes

Processes of SAP Solution Manager

SAP Solution Manager object type [Process](#), assigned to [Scenario](#) in the process structure in scope is included in synchronization. If the process contains process steps, all the steps in scope will also be synchronized. If the process is empty, then only the process name will be synchronized. Processes' attributes will be synchronized if they are mapped in a synchronization project and attribute types are supported by the connector.

Processes of SAP Signavio

SAP Signavio object type BPMN Diagram 2.0 that belongs to the process structure in scope is included in synchronization.

Note

If the folder in scope of synchronization contains other model types that are not BPMN Diagram 2.0 types, these models will be ignored in synchronization.

If the BPMN Diagram 2.0 is empty, then only the BPMN Diagram 2.0 name will be synchronized.

BPMN Diagram 2.0 attributes will be synchronized if they are mapped in synchronization project and attribute types are supported by the connector.

SAP Signavio BPMN Diagram 2.0 are mapped and synchronized to the process object type of SAP Solution Manager.

Note

Synchronization of BPMN 2.0 diagrams from SAP Signavio to SAP Solution Manager updates SAP Solution Manager process structure, not associated BPMN 2.0 collaboration and process diagrams. We recommend including links to SAP Signavio diagrams in synchronization to SAP Solution Manager. Access the latest BPMN 2.0 diagrams imported to SAP Solution Manager using the URL that is imported to the process node custom attribute.

Synchronization direction: SAP Signavio --> SAP Solution Manager

BPMN Diagram 2.0 object type in SAP Signavio is mapped and synchronized to process object type in SAP Solution Manager.

Initial import will create new processes in SAP Solution Manager under the right scenarios.

After initial synchronization, BPMN Diagram 2.0 object could be changed: renamed, copied, moved to a different Folder (scenario) in SAP Signavio.

Follow-up update synchronization will reflect the changes in SAP Solution Manager.

Note

BPMN Diagram 2.0 should be moved to a folder that is a scenario, rather than a folder that was previously synchronized with SAP Solution Manager folder object type.

Synchronization direction: SAP Solution Manager --> SAP Signavio

Process object type in SAP Solution Manager is mapped and synchronized to BPMN Diagram 2.0 object type in SAP Signavio.

After initial synchronization, processes synchronized to SAP Signavio at least once, must not be changed in SAP Solution Manager. The process must be changed in SAP Signavio, which is the leading tool for managing process changes, and synchronized via the follow up update synchronization run to SAP Solution Manager. Only associated elements of process (such as assigned documents, executables, and attributes that are not in scope of synchronization) can be still changed in SAP Solution Manager.

Note

BPMN Diagram 2.0 objects that were synchronized to SAP Solution Manager at least once, must not be deleted in SAP Signavio. If BPMN Diagram 2.0 object is no longer required, consider creating a new Folder (scenario) called **Archived Models** and move the BPMN Diagram 2.0 object into this folder.

If BPMN Diagram 2.0 objects are deleted, synchronization will be inconsistent and the process object in SAP Solution Manager won't change.

📌 Note

Initial SAP Solution Manager --> SAP Signavio synchronization imports SAP Solution Manager diagrams collaboration and process diagrams assigned to SAP Solution Manager process node as a new revision of the process model.

4.3 Import of BPMN Diagram from SAP Solution Manager

Learn about the conditions affecting diagrams imported from SAP Solution Manager.

Both SAP Signavio and SAP Solution Manager use BPMN 2.0 diagrams for process modeling. The diagrams contain *Tasks* or *Process Steps* that are logically connected as a process flow using other objects of BPMN 2.0 conventions.

In SAP Solution Manager, the same process definition can be represented as several, equally-valid visual process diagrams.

In SAP Signavio Process Manager, there is no separation between processes and process diagrams. If in SAP Solution Manager there are multiple diagrams of the same process, these diagrams are imported as a new revision of the process model.

The process model represents the process in the structure of SAP Solution Manager and contains all process steps visible as process step nodes in the structure. Every other revision of the process model represents either collaboration diagrams or process diagrams. Diagram revisions can be restored, updated and synchronized back to SAP Solution Manager. The updates are only reflected in the process structure. The collaboration and process diagrams graphical view is not updated in synchronization from SAP Signavio to SAP Solution Manager. The new steps are not reflected in the diagrams, though changes to process and process steps names are visible due to the default function of SAP Solution Manager.

The following types of diagrams are supported:

- Process Diagram
- Collaboration Diagram

Both diagrams will be imported to the same object type in SAP Signavio known as *Business Process Model Diagram BPMN 2.0*.

Updates to collaboration and process diagrams assigned to the process nodes of SAP Solution Manager are not supported.

→ Tip

We recommend maintaining modeling in SAP Signavio. After initial import of SAP Solution Manager diagrams to SAP Signavio is successful, we recommend discarding or archiving all imported collaboration and process diagrams in SAP Solution Manager and continue modeling in SAP Signavio only.

4.4 Importing Models to SAP Solution Manager

Learn how to synchronize models in the direction: SAP Signavio --> SAP Solution Manager.

Prerequisites

You checked that all SAP Signavio models, which you want to have synchronized, are in the correct *Model revision state*, such as one of the options shown in Step 3. While the states such as *approved* or *published* are customizable to your needs, the synchronization happens for models of your **one** selected *Model revision state* only. SAP Signavio models of other revision states will be skipped during synchronization.

Context

You can synchronize models from SAP Signavio Process Manager using model revision state that is configured in SAP Signavio Process Governance workflow to SAP Solution Manager. You can exclude unfinished models by specifying to synchronize a specific model revision state used for approved models, which are ready to be imported to SAP Solution Manager.

You can also include Variant Management information to be imported to SAP Solution Manager if the optional settings are configured in the sync project.

Procedure

1. From the business process model connector for SAP Signavio solutions home screen, choose the *Synchronization projects* tile.
2. Select your synchronization project name from the list.
3. Define the source of your model revision state as enabled in the selected workspace.

Note

- By default, SAP Signavio Process Manager is selected for an **existing, active synchronization project**. With no changes made to your existing project, synchronization uses the latest model revision. All models from the latest revision are imported to SAP Solution Manager.
- If you select SAP Signavio Process Governance, you can also choose a desired model revision state for synchronization to SAP Solution Manager. For example, choosing the *approved* revision state excludes synchronization of models that are *in progress*. Only *approved* models are imported to SAP Solution Manager.

Indicate if SAP Signavio Process Governance is enabled in the selected workspace.

☐ SAP Signavio Process Manager
☒ SAP Signavio Process Governance

Model revision state*

Select a state

in progress

approved

published

rejected

Note

To be able to access the latest SAP Signavio BPMN model after import to SAP Solution Manager, follow these steps:

- Before importing the model, navigate to the [Map Attributes](#) tab.
- In the field [Link to SAP Signavio Model](#), choose SAP Solution Manager text attribute from the proposed list of attributes by typing its name. The chosen attribute will be used for holding a URL to SAP Signavio BPMN model.
- After importing the model to SAP Solution Manager, you can view the model's attributes and URL from your SAP Solution Manager system.
- Copy and paste the URL in a new browser window to access the model.

Note

Additional information for SAP Signavio variant management can be imported to SAP Solution Manager. Import of the following variant management elements is supported from SAP Signavio to SAP Solution Manager:

- Variant: An attribute to indicate if an imported process to SAP Solution Manager is a [Process Variant](#) or a [Process Template](#).
- Dimension: An attribute to map and import process dimensions to SAP Solution Manager.

For more information on how to map and import process variant management information to SAP Solution Manager, see [Synchronization of Variant Management \[page 24\]](#).

4. Confirm with [Include](#).

4.5 Synchronization of Variant Management

Learn details of synchronizing variant management information from SAP Signavio to SAP Solution Manager.

Synchronization direction: SAP Signavio --> SAP Solution Manager

If variant management is used to manage processes in SAP Signavio, then additional information for variant management can be imported to SAP Solution Manager. Import of the following variant management elements is supported from SAP Signavio to SAP Solution Manager:

- Variants: An attribute element to indicate if imported process to SAP Solution Manager is a *Process Variant* or a *Process Template*. A custom attribute in SAP Solution Manager must be manually created for managing variants information. The attribute is then used for mapping the variants in the synchronization project and used to synchronize variants information to SAP Solution Manager.
- Dimensions: Attributes element to map and import process dimensions to SAP Solution Manager. Multiple custom attributes in SAP Solution Manager must be manually created for managing dimensions information: one for each dimension. The attribute is then used for mapping the dimensions in the synchronization project and to synchronize dimension values to SAP Solution Manager.

To be able to import information about variant management from SAP Signavio to SAP Solution Manager, follow these steps:

1. From the synchronization projects wizard, select your project and navigate to the *Map Attributes* phase.
2. Select the *Variant Management* tab and provide mapping for the variant management fields.

Note

In the field *Variant Management (Process Template / Process Variant)*, choose SAP Solution Manager single line text attribute from the proposed list of attributes by typing its name. This attribute is used to show variant management information for the synchronized model to SAP Solution Manager.

1. Navigate to *Select SAP Signavio dimension* to map SAP Signavio variant management dimensions to an SAP Solution Manager custom attribute.
2. Enter the dimension name and select it from the proposed list.
3. For *Select SAP Solution Manager custom attribute*, choose SAP Solution Manager multi-value attribute from the proposed list by typing its name.

Note

The chosen attributes are used to show variant management dimensions information for the synchronized models to SAP Solution Manager.

After importing the process to SAP Solution Manager, you can view the process custom attributes with variant management information imported from your SAP Signavio system.

A variants attribute will have one of the following values:

- *Process variant*
- *Process template*
- *No variant management*

Dimensions attributes contain the values of the mapped and imported dimensions.

Note

Changes to variants and dimensions information in SAP Signavio imports the updates to processes attributes to SAP Solution Manager, according to synchronization project mapping. For example, if dimensions are removed and changed with new dimensions in SAP Signavio, the custom attributes will be updated after synchronization from SAP Signavio to SAP Solution Manager, reflecting the latest changes in SAP Solution Manager.

4.6 Synchronization of Process Steps

Check synchronization parameters for process steps originating from SAP Solution Manager and process step equivalents originating from SAP Signavio.

Process Steps from SAP Solution Manager

If the process structure for SAP Solution Manager has a *process step (reference)* assigned to it as a process object, then that *process step (reference)* is included in synchronization.

Synchronization Direction: SAP Solution Manager --> SAP Signavio

- An SAP Solution Manager *process step (reference)* object type is mapped to and synchronizes with an SAP Signavio *task* object type. A *process step (reference)* becomes a *task*.
- When a *process step (reference)* is imported to SAP Signavio, its new SAP Signavio *task* ID is the same *process step (reference)* ID from SAP Solution Manager.
- After initial synchronization, the *task* can be renamed, copied, or moved to a different BPMN Diagram 2.0.

Process Step Equivalents from SAP Signavio

If the *dictionary (activity)* for SAP Signavio has a BPMN Diagram 2.0 *task* mapped to it, that *task* is included as a process step equivalent in synchronization.

SAP Signavio has the following mapping conditions:

- Only one dictionary category can be used for all *tasks*.
- *Tasks* must belong to the main category and not a sub-category.

Synchronization direction: SAP Signavio --> SAP Solution Manager

- An SAP Signavio *task* object type is mapped to and synchronizes with an SAP Solution Manager *process step (reference)* object type. A *task* becomes a *process step (reference)*.
- When a *task* is imported to SAP Solution Manager, its new *process step (reference)* ID is the same *task* ID from SAP Signavio.

- After initial synchronization, the *process step (reference)* can be renamed, copied, or moved to a different SAP Solution Manager process.

📘 Note

To avoid receiving warning notifications, map all *tasks* to the *dictionary (activity)* before synchronization starts. A synchronization run excludes unmapped *tasks*.

To import excluded *tasks* after the initial synchronization, map the *tasks* to the *dictionary (activity)* and run an update synchronization.

Attributes of Process Steps and Tasks

Attributes of SAP Solution Manager *process steps (reference)* and SAP Signavio *tasks* are included in synchronization under the following conditions:

- The attributes are mapped in the synchronization project.
- The attribute types are supported by the business process model connector for SAP Signavio solutions.

Related Information

[Synchronization Objects and Functionality \[page 16\]](#)

4.7 Synchronization of Linked Diagrams to SAP Solution Manager

Learn about synchronizing linked diagrams from SAP Signavio by importing **process links** to SAP Solution Manager.

Linked Diagrams in SAP Signavio

BPMN diagrams that are imported to SAP Solution Manager can have linked diagrams in SAP Signavio. There are several ways to create a link between diagrams in SAP Signavio. Objects like *Collapsed Subprocess*, *Intermediate Link Events* (catching and throwing), and *Custom Attributes* can be used to link diagrams.

If a synchronized BPMN diagram has any linked diagrams, the links are displayed in the side panel's *Linked diagrams* section.

Example

The screenshot shows the SAP Solution Manager interface for 'Process 1'. On the left, a diagram shows three process steps: Process 1.1, Process 1.2, and Process 1.33. Below the diagram is a table with columns: Name, Type, Description, and Created. The table contains one entry: 'Process 1' (Draft), BPMN, 27 Mar 2025. On the right, a sidebar shows 'Process 1' details. Under 'Link NJ100', there is a list of linked diagrams: Process 1.55, Process 1.1, Process 1.55, Process 1.2, and Process 1.33. The 'Linked diagrams' section is highlighted with a red box.

Process Links in SAP Solution Manager

In SAP Solution Manager, *Process Link* objects represent links from the selected process to other processes.

Example

The screenshot shows the SAP Solution Manager interface for 'Process 1'. The top part shows a tree view with folders: Folder 1 update, Sub-Folder 1, Scenario 2, and Scenario 1. Below the tree is a table with columns: Name, Type, Group, and Path. The table contains four entries: Process 1.2, Process 1.33, Process 1.1, and Process 1.55. All entries are of type 'Process <Link>' and are grouped under 'Process Links'. The paths are all the same: '/Solution/Business Processes/DEMO KTFolder 1 update/Sub-Folder 1/Scenario 1'.

Linked diagrams created in SAP Signavio for the synchronized BPMN diagram are imported to SAP Solution Manager as *Process Link* objects.

Synchronization of Linked Diagrams

You can automatically import linked diagram objects with an initial or update synchronization.

Note

Before synchronization, ensure all SAP Signavio models and linked diagrams that you want to synchronize, are located in the right part of the process structure and are ready for synchronization, as described in [Importing Models to SAP Solution Manager \[page 22\]](#).

Example

Status	Phase	Step
Completed	Sync Process Structure	Sync Folder and Scenario's
Completed	Sync Process Structure	Sync Process Steps
Completed	Sync Process Structure	Sync Process Links

Messages for selected step (3 / 3)

Status	Message
Success	Process Link assignment was created for PROCESSMODEL with name Process 1 and ID 5003e84de809752c51b564 - created assignment with name Process 7.7 and ID 6b2b4fda23a745cd8dd9bba9f28a12fa
Success	Process Link assignment was deleted from PROCESSMODEL with name Process 1 and ID 5003e84de809752c51b564 - deleted assignment with name Process 1.55 from attribute and ID d1ad43724da14019bf6df494c14227ea
Success	Process Link assignment was deleted from PROCESSMODEL with name Process 1 and ID 5003e84de809752c51b564 - deleted assignment with name Process 1.33 and ID 21f514ca34ad497b8bb9d54bb6ba9bc8

You can delete linked diagrams of the synchronized BPMN diagram in SAP Signavio and run an update synchronization. As a result, corresponding [Process Link](#) objects are deleted in SAP Solution Manager. In the import login [Phase 3](#), a log message confirms the deletion of the linked diagrams.

You can import a linked diagram only if the diagram in SAP Signavio is located within the synchronized folder structure. An SAP Solution Manager process that is linked using the [Process Link](#) object must exist as a process in the process structure synchronized between SAP Signavio and SAP Solution Manager. The linked process must exist in the sync folder structure before a corresponding [Process Link](#) can be created.

Note

When you run an **initial synchronization** of processes from SAP Solution Manager to SAP Signavio, synchronization of [Process Links](#) from SAP Solution Manager to SAP Signavio is not supported and [Process Links](#) are not included.

Adding the same diagram links to synchronized diagrams in SAP Signavio and running an update synchronization from SAP Signavio to SAP Solution Manager creates new [Process Link](#) objects in SAP Solution Manager. The update synchronization does not replace the original [Process Link](#) objects in SAP Solution Manager.

After initial synchronization from SAP Solution Manager to SAP Signavio is complete, any required links between BPMN diagrams must be created in SAP Signavio. All [Process Links](#) that exist in SAP Solution Manager upon the initial import of processes to SAP Signavio must be maintained in SAP Signavio before an update synchronization of diagram links to SAP Solution Manager takes place.

Manual deletion of synchronized [Process Links](#) in SAP Solution Manager is not supported and can lead to data inconsistency. If a [Process Link](#) is deleted directly in SAP Solution Manager, it is not recreated with an update synchronization from SAP Signavio to SAP Solution Manager.

4.8 Synchronization of Dictionary (Activity) and Process Step Library

Learn about the conditions for synchronizing SAP Signavio dictionary objects and SAP Solution Manager library objects.

The following object types from SAP Signavio dictionary and SAP Solution Manager library are included in synchronization:

SAP Signavio Dictionary	SAP Solution Manager Library
<i>Dictionary (Activity)</i> object types	<i>Process step (original)</i> object types

Attributes of *process step (original)* and *Dictionary (Activity)* objects are included in synchronization under the following conditions:

- The attributes are mapped in the synchronization project.
- The attribute types are supported by the business process model connector for SAP Signavio solutions.

Synchronization Direction: SAP Signavio --> SAP Solution Manager

An SAP Signavio *Dictionary (Activity)* category or sub-category is mapped to and synchronizes with a *process step (original)* in SAP Solution Manager's process step library.

- Only one *Dictionary (Activity)* category or sub-category can be mapped. If *Dictionary (Activity)* category is mapped, then only objects from this mapped category and not the objects from its sub-categories are included in synchronization.
- Synchronization creates *process steps (original)* objects in the process step library's main folder only: *Library -> Process Step Library*. After synchronization, you can move imported *process steps (original)* into the library's sub-folders.
- After synchronization, you can change an SAP Signavio *Dictionary (Activity)* object's name, description, or other attributes within the scope of synchronization. The next update synchronization changes the corresponding *process step (original)* in SAP Solution Manager, either in the process step library's main folder or a sub-folder where the imported object is located.

If SAP Signavio *Dictionary (Activity)* used in synchronization contains duplicated or obsolete objects, the objects can be merged in the *Dictionary (Activity)* in SAP Signavio. Remaining objects are synchronized to SAP Solution Manager in the initial synchronization.

If merged objects were synchronized to SAP Solution Manager before merging took place in SAP Signavio, then both remaining and old objects are still visible in SAP Solution Manager process step library. Deletion or merging objects in SAP Solution Manager through synchronization is not supported.

After merging *Dictionary (Activity)* objects, its associated tasks might have changed or might need to be removed from the BPMN 2.0 diagrams used in synchronization in SAP Signavio. All changes to the diagrams as a result of merging *Dictionary (Activity)* objects are synchronized to SAP Solution Manager as normal, supporting updates to the process and its associated process steps. If any of the tasks were removed from the diagrams as a result of *Dictionary (Activity)* merge, a deletion flag for tasks can be used to reflect this in SAP Solution Manager in an update synchronization.

Dictionary (Activity) category used for synchronization can be renamed if required in SAP Signavio before update import to SAP Solution Manager.

Note

If *Dictionary (Activity)* was renamed in SAP Signavio, then the synchronization project needs to be manually updated to map the new name of the *Dictionary (Activity)* to keep the changes consistent. The new name of *Dictionary (Activity)* can be selected and updated in the *Proposed dictionary category* field. By typing the new name in the field, the name is visible and can be selected.

Synchronization Direction: SAP Solution Manager -> SAP Signavio

An SAP Solution Manager *process steps (original)* object is mapped to and synchronizes with *Dictionary (Activity)* in SAP Signavio.

- *Process steps (original)* located in either the library's main folder or a sub-folder **are included** in the synchronization and mapped to SAP Signavio dictionary.
- Synchronization creates *Dictionary (Activity)* objects in the mapped dictionary category or sub-category.
- In the synchronization project, you can select the preferred category *Dictionary (Activity)* since it already exists in SAP Signavio. Alternatively, specify a new custom category and the business process model connector for SAP Signavio solutions creates it automatically. We recommended that only workspace administrators get access to create and manage the dictionary category.

Related Information

[Mapping Objects \[page 58\]](#)

4.9 Synchronization of Executables

Learn about the synchronization of SAP Solution Manager executables and their assignments to process steps.

Import Executable Library to SAP Signavio

If SAP Solution Manager contains *Executable <Orig.>* objects, then those objects can be imported to SAP Signavio. Importing executables is optional for running a synchronization project.

For more information about SAP Solution Manager executables, see [Executable Library](#).

Key Points for Importing Executables

- Import direction: SAP Solution Manager --> SAP Signavio
- Location of SAP Solution Manager executables: ► [Library](#) ► [Executable Library](#) ►
- Executables object types: [Executable <Orig.>](#) (in SAP Solution Manager executable library) are represented by [Others](#) (in SAP Signavio dictionary).

Note

[Executable <Orig.>](#) objects originate from SAP Solution Manager and must be managed and updated in SAP Solution Manager only.

Prerequisites

- You manually created [Dictionary Category \(Others\)](#) in SAP Signavio to receive [Executable <Orig.>](#) objects from SAP Solution Manager.
- New sync project: You mapped [Dictionary Category \(Others\)](#) in the new connector sync project.
- Existing sync project: You mapped [Dictionary Category \(Others\)](#) in an existing sync project previously used to synchronize process structure content.


Note

Import of [Executable <Ref.>](#) objects assigned to [Tasks](#) and [Activities](#) is only possible if [Dictionary Category \(Others\)](#) is mapped for import of [Executable <Orig.>](#), as described in the prerequisites.

Importing Executables from SAP Solution Manager

After mapping the sync project as described in the *Prerequisites* section, you can import [Executables <Orig.>](#) from the executables library in SAP Solution Manager to [Dictionary \(Others\)](#) in SAP Signavio.

1. Run a synchronization project as described in [Running a Synchronization \[page 67\]](#).
2. Choose [Import Executable Library to SAP Signavio](#).



Updating Executables

After the initial [Executable <Orig.>](#) import, do not attempt to manually change any imported [Dictionary \(Others\)](#) objects in SAP Signavio. If changes to executables are needed, a subsequent **update** import must be triggered from the executable library in SAP Solution Manager.

→ Tip

We recommend making regular updates of the executable library from SAP Solution Manager to SAP Signavio. This ensures that all [Executable <Orig.>](#) objects needed for process modelling are available in the dictionary of SAP Signavio.

To update [Executable <Orig.>](#) in SAP Signavio, follow these steps:

1. Run a synchronization project as described in [Running a Synchronization \[page 67\]](#).
2. Choose *Import Executable Library to SAP Signavio*.

📘 Note

An update of *Executable <Original>* from SAP Solution Manager to SAP Signavio applies the following conditions:

- New executables are added to SAP Signavio.
- Any executables deleted in SAP Signavio are recreated.
- Any executables deleted in SAP Solution Manager are not deleted from SAP Signavio, but remain in the dictionary instead.

Formats of Imported Executables

All executable object types can be imported to SAP Signavio. The imported object uses a format shown in the chart below, where either the executable name or object is displayed in the title of the imported object and additional information is displayed in the description.

SAP Solution Manager Executable type	Attribute in SAP Solution Manager	Attribute in SAP Signavio
Transaction Program	Object	Title (standard attribute)
	Name	Description (standard attribute)
	Type	Description (standard attribute) - new line under Name
	Logical Component Group	Description (standard attribute) - new line under Type
	Link (URL) to Executable Library objects	Relevant Documents (standard attribute)
BSP Application CRM People-Centric UI CRM WebClient Application Custom URL Java Web Dynpro Success Factors Application URL Web Dynpro ABAP Apps. Config Web Dynpro ABAP Application	Name	Title
	Object	Description (standard attribute)
	Executable Type	Description (standard attribute) - new line under object
	Logical Component Group	Description (standard attribute) - new line under type
	Link (URL) to Executable Library objects	Relevant Documents (standard attribute)
Job Documentation	Name	Title
	Object	Description (standard attribute)
	Executable Type	Description (standard attribute) - new line under object
	Version	Description (standard attribute) - new line under type
	Logical Component Group	Description (standard attribute) - new line under version
	Link (URL) to Executable Library objects	Relevant Documents (standard attribute)
Fiori Application	Name	Title
	Object	Description (standard attribute)
	Executable Type	Description (standard attribute) - under object
	Fiori ID	Description (standard attribute) - under Type
	Action	Description (standard attribute) - under Fiori ID
	Logical Component Group	Description (standard attribute) - under Action
	Link (URL) to Executable Library objects	Relevant Documents (standard attribute)

Note

When the executable *Name* is empty in SAP Solution Manager, but not the executable *Object*, the *Object* is then reused to prevent a blank executable *Title* in SAP Signavio.

Optional Synchronization Actions

Import of executables is optional. In the *Map Dictionary* section of a new sync project, leave the mapping fields for *Dictionary Category (Others)* blank if you do not need to import executables. For an update synchronization with an existing sync project, if the import of executables has happened at least once, changes are not possible for the already-mapped *Dictionary Category (Others)*.

Optional dictionary categories and object types

Please select required Dictionary category from SAP Signavio

Optional dictionary category	Dictionary category type	Object type	Area
SAP Executables (DEMO)	Others	Executable	Executable Library

[Dictionary Category \(Others\)](#) can be renamed in SAP Signavio, if needed. The sync project using the renamed category must be updated manually. After a successful synchronization run, if the renamed category was not manually updated, dictionary names may not match SAP Signavio and the connector sync project.

Import of Executable Assignments to SAP Signavio

Executables assigned to [Process Step <Orig.>](#) and [Process Step <Ref.>](#) in SAP Solution Manager are both [Executable <Ref.>](#) object types. These object types can be imported from SAP Solution Manager to [Activity \(Dictionary\)](#) and [Tasks](#) in SAP Signavio as executable assignments. Importing executable assignments is optional for running a synchronization project.

SAP Solution Manager		SAP Signavio	
Process object type	Executable object type	Process object type	Executable object type
Process Step <Orig.>	Executable <Ref.>	Activity (Dictionary)	Attribute Dictionary Link (list)
Process Step <Ref.>	Executable <Ref.>	Task	Attribute Dictionary Link (list)

Rules for Mapping Executable Assignments

- The attribute [Dictionary Link \(List\)](#) requires the selection scope of [Only for](#) the executables dictionary in the sync project.

- If [Executables Dictionary \(Others\)](#) is mapped in the sync project, then the [Dictionary Link \(List\)](#) attribute must select objects from that dictionary only.
- The attribute must be assigned in SAP Signavio to [Dictionary \(Activity\)](#) for synchronization of [Process Steps <Orig.>](#).
- The attribute must be assigned in SAP Signavio to [Tasks](#) for synchronization of [Process Step <Ref.>](#).

Note

For executable assignments, the same attribute is used for [Task](#) and [Activity \(Dictionary\)](#).

Prerequisites

- You manually created the attribute [Dictionary Link \(List\)](#) in SAP Signavio.
- You mapped the attribute in the sync project from [Map Attributes](#).

Recommended		Customized	
Process Manager Attribute		Solution Manager Attribute	
☐ Documentation	Used in: BPMN Task	Description	Used in: REF_PROCTSTEP PROC
☐ Task Type	Used in: Task	Task Type	Used in: REF_PROCTSTEP

Note

If an import of executable assignments is not needed, the attribute mapping for executables section can be left blank.

Importing Executable Assignments from SAP Solution Manager

To import *Executables* <Ref.> from SAP Solution Manager to SAP Signavio as assignments of *Activity* (*Dictionary*) and *Tasks*, follow these steps:

1. Run a synchronization project as described in [Running a Synchronization](#) [page 67].
2. Choose *Import Executable Library to SAP Signavio*.
3. Choose *Initial import of Executable assignments to SAP Signavio Tasks and Activities*.



→ Tip

We recommended running the initial import of executable assignments from SAP Solution Manager to SAP Signavio only. All updates to executable assignments after initial import should take place in SAP Signavio only. Removing and adding new assignments on *Tasks* and *Activities* should take place in SAP Signavio.

For a follow-up import of executable assignments, all executables assigned using *Dictionary Link (List)* are overwritten according to the following rules:

- New assignments from SAP Solution Manager are added.
- Removed assignments in SAP Solution Manager are deleted from the dictionary link attribute used for executable assignments for *Tasks* and *Activities* in SAP Signavio.
- Any executable assignments created locally in SAP Signavio between the previous and the current synchronization are removed.

Note

The rules for updating of the executable library also apply, as described earlier in this section.

Import of Executables for Already-Existing Synchronization Project

If the import of executables is needed when there is an active sync project already used for synchronization of processes, the existing sync project must be edited. Namely, mapping of *Dictionary* (*Other*) and executables assignments attributes must be added to the sync project. The import of executables for an already-existing sync project is optional if the required executable assignments from an initial import (SAP Solution Manager to SAP Signavio) can be selected.

For the existing project, *Activities* (*Dictionary*) and *Tasks* objects that are already synchronized between SAP Solution Manager and SAP Signavio can be enhanced with executable assignments. An import of executables

❖ Example

After mapping the synchronization project, we recommend synchronizing the process structure first, then importing executables after the structure import finishes.

The following scenarios show how executables can be imported with existing sync projects:

- Initial synchronization of SAP Solution Manager --> SAP Signavio, followed by an import of executables to SAP Signavio.
- Initial synchronization of SAP Solution Manager --> SAP Signavio, update processes in SAP Signavio, synchronize updates to SAP Solution Manager, assign executables to process steps in SAP Solution Manager, import of executables with or without assignments to SAP Signavio.
- Initial synchronization of SAP Signavio --> SAP Solution Manager, enhance and update imported process steps with executables in SAP Solution Manager, import of executables to SAP Signavio with or without executables assignments.

After import of *Executable <Orig.>* from SAP Solution Manager to SAP Signavio is complete, the objects are available in *Dictionary (Other)*. These objects can be assigned as a dictionary link in SAP Signavio to *tasks* and *activities* as executable assignments. If tasks and activities already have imported from SAP Solution Manager executable assignments, the assigned objects can be changed, if required, by adding or removing executable assignments in the *Dictionary Link (List)* attribute, which is used for mapping assignments.

All updates to executable assignments after initial import from SAP Solution Manager to SAP Signavio, should take place in SAP Signavio only. Removing and adding new assignments on tasks and activities should take place in SAP Signavio. The updates can then be imported to SAP Solution Manager.

Synchronization logs display logs of all objects synchronized to SAP Solution Manager, including executable assignments linked to [Tasks](#) and [Activities \(Dictionary\)](#).

C30		fx							
		A	B	C		D		E	
1	Sync Project ID	9abb8c293-ef25-4b1d-88f8-16e48df1516e							
2	Sync Run ID	559921c1f-84f8-4b0e-aac8-d4cf70c0f19d							
3									
4									
5	Status	Step	Message				Start	End	
6	Success	Validate Sync project data	Project Validation successful				01/20/2025 10:18:10	01/20/2025 10:18:10	
7	Success	Create Signavio and Solman Object Mapping	Project Storage Initialization has completed				01/20/2025 10:18:13		
8	Success	Sync Folder and Scenario's	Sync completed for ObjectType: FOLDER with name Folder and ID 5cd99998c3d64105a83a1c6a687422ed				01/20/2025 10:18:16	01/20/2025 10:18:17	
9	Success	Sync Folder and Scenario's	Sync completed for ObjectType: FOLDER with name Scenario and ID 33ea3353e40072dbd6853d6c7f1c8				01/20/2025 10:18:17	01/20/2025 10:18:17	
10	Success	Sync Process Models	Sync completed for ObjectType: PROCESSMODEL with name Process and ID 72a33ae85f2cd6dbaa0d18365d114				01/20/2025 10:18:20	01/20/2025 10:18:21	
11	Success	Sync Process Steps	Sync completed for ObjectType: PROCSTEP with name proc step 1 and ID b42c021350f49d56b1c7f36e74165				01/20/2025 10:18:22	01/20/2025 10:18:22	
12	Success	Sync Process Steps	Sync completed for ObjectType: PROCSTEP with name proc step 2 and ID 061a0761b3d44f77b5a18d126b2a419				01/20/2025 10:18:24	01/20/2025 10:18:23	
13	Success	Sync Process Steps' Executable Links	Executable assignment was deleted from Activity with name proc step 1 and ID To4fmnh7jlmjmbGvG - deleted assignment with name VAO1 and ID 6ef0a81c8f214261464370d06993a5c7				01/20/2025 10:18:26	01/20/2025 10:18:26	
14	Success	Sync Process Steps' Executable Links	Executable assignment was deleted from Activity with name proc step 2 and ID To4fmnh7jlmjmbGvG - deleted assignment with name VAO1 and ID 6ef0a81c8f214261464370d06993a5c7				01/20/2025 10:18:26	01/20/2025 10:18:26	
15	Success	Sync Process Steps Reference	Sync completed for ObjectType: REF_PROCSTEP with name proc step 1 and ID REF_To4fmnh7jlmjmbGvG				01/20/2025 10:18:29	01/20/2025 10:18:29	
16	Success	Sync Process Steps Reference	Sync completed for ObjectType: REF_PROCSTEP with name proc step 2 and ID REF_To4fmnh7jlmjmbGvG				01/20/2025 10:18:29	01/20/2025 10:18:29	

To learn how to access synchronization logs, see [Synchronization History \[page 71\]](#).

In addition, executable assignments logs can be found in synchronization run phase 4, *Process models*.

Example

Demo Sync Project Completed

1 Sync Initialization — 2 Process objects — 3 Process structure — **4 Process models** — 5 Diagrams and links

4. Process models

Status	Step	Message	Start	End
Completed	Sync Process Models	Sync Process Steps	20/01/2025, 10:18:21	20/01/2025, 10:18:23
Completed	Sync Process Models	Sync Process Steps' Executables Links	20/01/2025, 10:18:23	20/01/2025, 10:18:26
Completed	Sync Process Models	Sync Process Steps Reference	20/01/2025, 10:18:26	20/01/2025, 10:18:29
Completed	Sync Process Models	Sync Process Steps Reference' Executables Links	20/01/2025, 10:18:29	20/01/2025, 10:18:32

Messages for selected step (2 / 2)

Status	Message	Start	End
Success	Executable assignment was deleted from Activity with name proc step 1 and ID To4Fmh7j[mhNb]YdVG - deleted assignment with name VA01 and ID 6ef5a81c8f24261a64370d06993a5c7	20/01/2025, 10:18:26	20/01/2025, 10:18:26
Success	Executable assignment was deleted from Activity with name proc step 2 and ID To4Fmh7j[mhNb]LS7VG - deleted assignment with name VA01 and ID 6ef5a81c8f24261a64370d06993a5c7	20/01/2025, 10:18:26	20/01/2025, 10:18:26

Updates of executable assignments in SAP Signavio are imported to SAP Solution Manager as follows:

Executable Assignment Type	Condition	Result
Newly-assigned executables	If the objects are assigned directly to the task -->	Then executables are imported to <i>Process Step <Ref.></i> as new <i>Executable <Ref.></i> objects.
Newly-assigned executables	If the objects are assigned directly to the activities and are visible in SAP Solution Manager in the <i>Process Step <Ref.></i> as <i>Executable <Ref.></i> objects -->	Then executables are imported to <i>Process Step <Orig.></i> as new <i>Executable <Ref.></i> objects.
Removed executables	If assigned directly to tasks, but not to <i>Activity (Dictionary)</i> -->	Then <i>Executable <Ref.></i> is removed in SAP Solution Manager in the <i>Process Step <Ref.></i> corresponding to the task.
Removed executables	If assigned directly to <i>Activity (Dictionary)</i> -->	Then <i>Executable <Ref.></i> is removed in SAP Solution Manager in the <i>Process Step <Orig.></i> corresponding to the activity.
Removed executables	If assigned directly to <i>Activity (Dictionary)</i> in the task, but not in the activity -->	Then executables are not imported to SAP Solution Manager.

Note

Removing *Executable <Ref.>* in SAP Solution Manager in the *Process Step <Ref.>* that belongs to *Process Step <Orig.>* is not supported.

As a result, warning message is displayed.

Executable Assignment Type	Condition	Result
Manual changes to executables	If <i>Executable <Ref></i> is assigned to <i>Process Step <Ref.></i> and <i>Process Step <Orig.></i> in SAP Solution Manager -->	Then changes are not supported.

Note

If the objects are changed accidentally in SAP Solution Manager, but no change took place for the task and executable assignment in SAP Signavio, the assigned objects can be restored in SAP Solution Manager only if corresponding objects in SAP Signavio are changed.

If a SAP Signavio task or executable assignment is not changed, the updates are skipped.

4.10 Synchronization of Attributes

Learn how attributes can be configured and mapped between SAP Signavio and SAP Solution Manager in the business process model connector for SAP Signavio solutions's synchronization project settings.

Attributes can be mapped for the following object types:

SAP Signavio object type	SAP Solution Manager object type
BPMN Diagram 2.0	Process
Task	Process Step (reference)
Activity (dictionary)	Process Step (original)

Attributes must be configured in both SAP Signavio and SAP Solution Manager systems before synchronization is configured for the above object types. Attributes that are relevant for synchronization must be configured in the source and target system using the same data element types. The name of the attribute itself can be different.

Synchronization direction: SAP Signavio --> SAP Solution Manager

The following attribute types are supported:

- Boolean --> Boolean
- Single-line text --> Single-line text
- Multi-line text --> Multi-line text
- Dictionary link --> Single-line Text
- Dictionary link (list) --> Multi-line text

Synchronization direction: SAP Solution Manager --> SAP Signavio

The following attribute types are supported:

- Boolean --> Boolean
- Single-line text --> Single-line text
- Multi-line text --> Multi-line text

Note

In the business process model connector for SAP Signavio solutions *Configure --> Mapping* attributes phase, all attributes are available for selection. Pick attribute types that are supported by the business process model connector for SAP Signavio solutions and are mapped to a compatible type in the target system.

- Only supported attributes can be selected for mapping.
- Unsupported attributes that are mapped cause the project activation to fail.
- Deleted attributes in SAP Signavio cause the project activation to fail.

Related Information

[Mapping Objects \[page 58\]](#)

<https://blogs.sap.com/2016/10/31/create-customer-attributes-elements-process-management-solman-7.2/> 

4.11 Supported Languages

For multi-language SAP Signavio Process Manager workspaces, the connector supports synchronization in one main language of the workspace only. The main workspaces' language can be different from English.

When objects are imported from SAP Signavio --> SAP Solution Manager, where SAP Signavio workspace is set to use multi-language, the objects are imported to SAP Solution Manager in the main workspace language. The objects names are not changed during the import and appear in SAP Solution Manager with the names shown in SAP Signavio under the main workspace language.

Note

In SAP Signavio, all objects must have names in the main workspace language, in addition to other languages in the multi-language workspace for successful synchronization from SAP Signavio --> SAP Solution Manager.

Objects can be imported from SAP Solution Manager to SAP Signavio in an original language other than English. The objects are imported in SAP Signavio under the main workspace language, even if the language is different from SAP Solution Manager. The objects names are not changed during the import and appear in SAP Signavio with the same names as shown in SAP Solution Manager.

4.12 Deletion of Synchronized Objects

Learn the limitations that come with deleting synchronized objects.

You can delete an SAP Signavio task used in BPMN 2.0 diagrams and activities in dictionary. When it comes to synchronizing with SAP Solution Manager to reflect the deletion, you can use a deletion flag.

- After deleting a **task** in SAP Signavio, a deletion flag to its corresponding *Process Step <Ref.>* in SAP Solution Manager can be imported.
- After deleting an **activity** in SAP Signavio, a deletion flag to its corresponding *Process Step <Orig.>* in SAP Solution Manager can be imported.

The deletion flag must be set to be used in the synchronization project.

Note

SAP Signavio tasks or *Activity (Dictionary)* objects are not deleted and removed in SAP Solution Manager. Instead, they are flagged for deletion. This helps to protect other objects assigned to the process steps from unintentional deletion through synchronization from SAP Signavio to SAP Solution Manager.

Only one custom attribute needs to be created in SAP Solution Manager and provided in the connector Sync Project for setting up a deletion flag for both tasks and activities (Dictionary). For more information on how to set and use deletion flag, see [Mapping Attributes and Setting the Deletion Flag \[page 60\]](#).

Any other object types that were synchronized at least once in SAP Signavio or SAP Solution Manager must not be deleted, including the following:

- Folders and Scenarios
- Models

Caution

If any synchronized folders or models object types are deleted in either SAP Signavio or SAP Solution Manager, an update synchronization from SAP Signavio to SAP Solution Manager may result in an error.

In SAP Signavio, additional folders could be created within the synchronization structure, called **Archived Objects**, to manage manual archiving of the folders and models that are no longer required.

In SAP Signavio, an additional prefix or term in the object name can be used to flag and identify the folders and models that are no longer required.

In SAP Solution Manager, the next follow up update synchronization reflects changes made in SAP Signavio. Objects that are changed and moved to the archived folders (folders, scenarios, or models) are transferred to the corresponding folder in SAP Solution Manager accordingly. The process structure and its objects should not be changed in SAP Solution Manager manually (outside of synchronization) because it can lead to inconsistencies.

4.13 SAP Solution Manager Scope in Synchronization

Learn how scope selection is relevant for synchronization from SAP Solution Manager to SAP Signavio only.

You can limit the imported content with Scopes. Scopes are defined in SAP Solution Manager. For more information, see [Scopes](#) .

Note

Due to some limitations of the connector when importing large data volumes from SAP Solution Manager to SAP Signavio, we highly recommend to use scope if your SAP Solution Manager branch content is too large and exceeds 100 MB. The size of one selected scope should not exceed 100 MB.

If a scope for the import is not selected, the full branch content is used as the basis for all imports.

When you limit the imported content with a scope, your scope must include the folder that the export created. All following exports update the content of that folder.

Multiple scopes can be imported from SAP Solution Manager to SAP Signavio to support gradual import of large data.

If multiple scopes are used for import of large data volumes, the scopes must share one common top root folder in SAP Solution Manager. Already-imported processes in SAP Signavio must not be changed until full import of data for all scopes is complete.

If content is not included in the scope, this content will not be updated during later imports.

5 Connect

Establish connectivity between the connector application and the source systems that require regular synchronization.

To exchange updated process information between SAP Signavio Process Manager and SAP Solution Manager as source systems, the following direct connection conditions apply:

- **The connector** supports multi-system connectivity. More than one workspace from SAP Signavio Process Manager and more than one SAP Solution Manager system can exchange data using the connector.
- **Source systems** must connect with only one connector. Single-connector connectivity prevents any data duplication and inconsistent data transfer issues.

The following sub-topics describe how to set up connectivity of SAP Signavio Process Manager and SAP Solution Manager to the newest version of the connector application, called the business process model connector for SAP Signavio solutions.

⚠ Caution

Connect your source systems to the business process model connector for SAP Signavio solutions (the new connector) only.

Ensure that your source systems don't maintain a persisting connection with a second connector (the classic connector).

If you currently use the classic connector to synchronize SAP Signavio and SAP Signavio Process Manager as source systems, migrate your synchronized data using the business process model connector for SAP Signavio solutions, as described in SAP Note [3656181](#). Migrating classic connector data is mandatory due to the upcoming decommission of the classic connector. After migration, make subsequent synchronization updates with the business process model connector for SAP Signavio solutions only.

If you need technical support with data migration, create a support ticket with [SAP Signavio Support](#) and reference component BPI-SIG-CA-BMB.

[Connecting Signavio Process Manager \[page 43\]](#)

Learn how an SAP Signavio Process Manager system is connected using systems details that must be provided in the *System Configuration* area.

[Connecting SAP Solution Manager \[page 46\]](#)

Learn how SAP Solution Manager system is connected using systems details that must be provided in the *System Configuration* area.

[Creating the Trust Relationship \[page 52\]](#)

How to create the cloud to on-premise trust in the Cloud Connector.

Note

Here the system conducts a workspace validation check to prevent data duplication and inconsistent data transfer (as described in [Connect \[page 42\]](#)). Select an open space outside the form fields to initiate the workspace validation.

- A successful validation allows you to continue with the [Add System](#) process.
- If the validation is not successful, an error message opens:

Classic Connector Workspace Error

The Workspace/Tenant ID is already being used by the classic connector. Connecting this Workspace/Tenant ID to both connectors might lead to data loss or inconsistencies.

Please provide a different Workspace/Tenant ID if you would like to proceed with creation of SAP Signavio Process Manager system or alternatively, contact your connector administrator in case you need more support.

- **System Role:** Used to distinguish between test and production workspaces for documentation purposes.
- **Description:** It's recommended to use a short description because it appears in the list of connected systems.

5. Choose [Next](#).

[Technical Information](#) opens.

6. Enter the following information:

- **Host name** and **port number** are automatically defined based on the system header details.
- **Authentication type:** Basic or secure.
- **API user** and **password:** Use your usual login details for the specified workspace.

Note

For security and audit reasons, we recommended that this user is a technical user who is assigned an API license in SAP Signavio Process Manager.

7. Choose [Next](#).

This displays a summary of all provided information for review.

8. To complete the process, choose [Create System](#).

Results

After successful creation, the [Connected systems](#) view is displayed.

Task overview: [Connect \[page 42\]](#)

Related Information

[Connecting SAP Solution Manager \[page 46\]](#)

[Creating the Trust Relationship \[page 52\]](#)

5.1.1 Editing Connected System - SAP Signavio

Learn the steps to edit an SAP Signavio Process Manager system from the [Connected Systems](#) area.

Context

The system can be edited regardless of its [Active](#) or [Inactive](#) status, where [Active](#) status means the system is already used for synchronization.

The following system details can be edited for an already-connected system:


- System Name
- Description
- API User and Password

Note

The other system details related to the **workspace ID** and **location defining system main destination** cannot be edited. Connect a new system if those details require changing.

Procedure

1. From the connector application main menu, choose the tile [Connected Systems](#).
2. For the SAP Signavio system that needs to be edited, open the ellipsis menu for more options and choose [Edit](#).



3. Change required system information and choose [Next](#).
4. Confirm SAP Signavio username and password for edited system and choose [Next](#).

Note

Editing system details requires confirmation of the **API user** and **password**. These are not redisplayed on the edit system screen for security reasons.

If these credentials did not change, use the same as for the previous occasion. Otherwise, provide a new API user and password when editing system details.

5. Check that all systems information is correct on the summary page and confirm with [Update System](#).

Related Information

[Editing Connected System - SAP Solution Manager \[page 50\]](#)

5.2 Connecting SAP Solution Manager

Learn how SAP Solution Manager system is connected using systems details that must be provided in the [System Configuration](#) area.

Context

Please follow the steps in the [System Configuration](#) area to connect an SAP Solution Manager 7.2 system.

Multiple SAP Solution Manager systems can be created for these purposes:

- To connect your test and production SAP Solution Manager systems for validation.
- To connect multiple production SAP Solution Manager systems to support complex synchronization needs.

Procedure

1. From the connector application main menu, select the tile [Connected systems](#).
2. Choose [Add System](#).

This opens [Create System](#).


3. Select the system type [SAP Solution Manager](#).

The screenshot shows the 'Add System' form in the SAP Signavio application. The form is titled 'Define SAP Solution Manager header information' and includes the following fields and sections:

- System Type:** A dropdown menu with two options: 'SAP Signavio Process Manager' and 'SAP Solution Manager 7.2' (which is selected and highlighted in blue).
- System Name:** A text input field with the placeholder 'Type system name'.
- System ID:** A text input field with the placeholder 'Type system ID'.
- Client Number:** A text input field with the placeholder 'Type client number'.
- Support Package Stack:** A dropdown menu with the option 'Select a support package' and a downward arrow.
- Location ID:** A text input field with the placeholder 'Type location ID'.
- System Role:** A section with six buttons: 'Pre-Production', 'Production', 'Development', 'Test', 'Staging', and 'Sandbox'. The 'Test' button is currently selected.
- Description:** A text area with the placeholder 'Describe system here'.

4. Enter the following information (which can be found in SAP Solution Manager):

- **System Name:** Enter the common name used internally for this SAP Solution Manager system.
- **System ID:** Located in the bottom-right corner of SAP GUI (see screenshot).
- **Client Number:** Located in the bottom-right corner of SAP GUI (see screenshot).



- **Support Package Stack:** Located at ► [System Status](#) ► [SAP System data](#) ► [Installed Software](#) ► [SP Stack](#) ►

Business process model connector

Client Number*

Type client number

Support Package Stack*

Select a support package

System Status

System: Status

Usage data

Client: 0001

User:

Language: EN

Previous Logon:

Logon:

System time:

Time Zone: GMTUK

Number of Failed Password Logon Attempts: 0

SAP data

Repository data

SAP System data

Installed Software

Installed Software Component Versions

Installed Product Versions

Product	Release	SP Stack	Vendor	Short Description of Product Version
SAP SOLUTION MANAGER	7.2	08 (12/2018) FPS	sap.com	SAP SOLUTION MANAGER 7.2
FOCUSED BUILD AND INSIGHTS	2.0	03 (02/2019) FPS	sap.com	FOCUSED BUILD AND INSIGHTS 2.0

- **Location ID** (optional): Defined by the Cloud Connector administrator when connecting to the BTP subaccount.

Note

If the Cloud Connector has a location ID, it must be provided in the connector [Location ID](#) field or connectivity to SAP Solution Manager will not be successful.

Even though the Cloud Connector can be configured without a location ID, this field cannot be left blank for successful connectivity between the connector and SAP Solution Manager systems. The location ID must be configured in the Cloud Connector.

Caution

Ensure the underscore character (`_`) is not used as part of the location ID. In the connector, the location ID is used to generate the virtual hostname for the SAP Solution Manager system. If an underscore is used, connectivity to SAP Solution Manager is not possible.

- **System Role:** Look this up in the [Table T000](#) in SAP Solution Manager, or contact your system administrator.

Client	Name	City	Std. currency	Character Field Length = 10	Role
☐	000				S
☐	001				C
☐	066				S

Role	Short Descript.
P	Live
T	Test
C	Customizing
D	Demo
E	Training/Education
S	SAP reference

- **Description**

5. Choose [Next](#).

[Technical Information](#) opens.

6. Enter the following information:

- **Host name** and **Port number:** The same values you would use to log into SAP Solution Manager via web browser.
- **Service user** and **Password:** The credentials of the SAP Solution Manager service user.

→ Tip

If you don't have such a user, ask your system administrator to set one up. Ensure they allocate the roles as described in [Assigning Roles \[page 74\]](#) and [Necessary User Rights \[page 51\]](#).

- **Certificate type:** Select [Trusted](#) if your SAP Solution Manager has an officially-signed system certificate installed. Otherwise, select [Untrusted/Self-signed](#).

7. Choose [Next](#).

This displays a summary of all provided information for review.

8. To complete the process, choose [Create System](#).

Results

After successful creation, the [Connected systems](#) view is displayed.

Task overview: [Connect \[page 42\]](#)

Related Information

[Connecting Signavio Process Manager \[page 43\]](#)

[Creating the Trust Relationship \[page 52\]](#)

5.2.1 Editing Connected System - SAP Solution Manager

Learn the steps to edit an SAP Solution Manager system from the [Connected Systems](#) area.

Context

The system can be edited regardless of its [Active](#) or [Inactive](#) status, where [Active](#) status means the system is already used for synchronization.


The following system details can be edited for an already-connected system:

- System Name
- Description
- Support Package
- Location ID
- System Role
- Host Name
- Port Number
- Certificate Type
- System User and Password

Procedure

1. From the connector application main menu, select the tile [Connected Systems](#).
2. For your SAP Solution Manager system that needs to

be edited, choose more options () and choose [Edit](#).



3. Change required system header properties information and choose [Next](#).


Note

If you are editing the [Location ID](#), make sure it was required initially and use the right spelling conventions.

4. Change required system technical properties information.

→ Tip

As a best practice, use SAP BTP sub-account destination services to verify the system connection if you change your SAP Solution Manager system [Location ID](#) or technical property. Select your connected system and choose [Check Connection](#) within the [Destinations](#) section.



5. Confirm system user and password for the edited system and choose [Next](#).

ⓘ Note

Editing any system details would require confirmation of the system user and password. These are not redisplayed on the edit system screen for security reasons.

If these credentials didn't change, use the same as for the previous occasion. Otherwise, provide a new system user and password when editing system details.

6. Check that all systems information is correct on the summary page and confirm with [Update System](#).

Related Information

[Editing Connected System - SAP Signavio \[page 45\]](#)

5.2.2 Necessary User Rights

You need to enter credentials for a user in the connection setup. The rights this user needs can be system-specific.

To create the user in SAP Solution Manager, follow these steps:

1. In *User Maintenance*, create a new user, for example with the name **CONNECTOR**.
2. In *Logon Data*, set the *User Type* to *Service*.
3. In *Roles*, assign the following roles:
 - SAP_SM_SL_DISPLAY
 - SAP_SM_SL_EDIT_BPMN
 - SAP_SM_SL_ADMIN
4. Adjust the role SAP_SM_SL_ADMIN:
 1. Double-select SAP_SM_SL_ADMIN and create a copy.
 2. Add a prefix to the name of the copy, for example Z_SAP_SM_SL_ADMIN.
 3. In *Display Roles*, go to *Authorizations* > *Edit Authorization Data and Generate Profiles*.
 4. Navigate to *Solution Manager* > *Solution Administration* > *Activity*.
 5. Double-select the description text ("Create or generate...") next to *Activity*.
 6. Enable activity 61 *Export*.
 7. Save and generate the adjusted role.
5. Save the user.

5.3 Creating the Trust Relationship

How to create the cloud to on-premise trust in the Cloud Connector.

Context

Creating the trust relationship is a required step. It allows SAP Solution Manager to be accessed via the connector on SAP Business Technology Platform (SAP BTP).

→ Remember

This task should be performed by the person responsible for the Cloud Connector administration.

Procedure

1. Open *Cloud Connector Administration*.
2. In *Subaccount*, enter the subaccount that you created.
3. From the sidebar, select *Cloud To On-Premise*.
4. Under the *Access Control* tab, choose the plus symbol + above the *Mapping Virtual To Internal System* table.
5. Add the following information:

- **Backend type:** ABAP System
- **Protocol:** HTTPS
- **Internal Host:** <actual hostname>
- **Internal Port:** <actual HTTPS port>
- **Virtual Host:** <host from SAP Solution Manager details screen in the connector application>
- **Virtual Port:** <actual HTTPS port number>
- **Principal Type:** None
- **Host in req Header:** Internal Host
- **Description:** <your description of the mapped system>

A new virtual internal system is added that can be accessed from the subaccount.

6. Under the [Access Control](#) tab, choose the plus symbol + above the [Resources](#) table.
7. Add the following two resources:
 - a. In both cases, ensure [Active](#) is ticked and [Access Policy](#) is set to 'Path and All Sub-Paths'.

URL Path	Description
/sap/opu/odata/sap/ProcessManagement	SolMan ProcMgmt API
/sap/bc/icf/info	System Info API

Results

The trust relationship is established.

Task overview: [Connect \[page 42\]](#)

Related Information

[Connecting Signavio Process Manager \[page 43\]](#)

[Connecting SAP Solution Manager \[page 46\]](#)

6 Configure

Learn how synchronization settings are configured.

Steps for configuring synchronization settings:

- Creating a synchronization project.
- Mapping SAP Signavio Process Manager dictionary categories and their object types to corresponding object types in SAP Solution Manager.
- Mapping SAP Signavio Process Manager attributes to their corresponding attributes in SAP Solution Manager.

[Creating a Synchronization Project \[page 54\]](#)

Learn how to create a synchronization project for each SAP Signavio Process Manager workspace and SAP Solution Manager solution that are to be synchronized together.

[Editing a Synchronization Project \[page 56\]](#)

Learn how to make changes to your synchronization project and avoid synchronization run errors.

[Mapping Objects \[page 58\]](#)

Learn how to map *activity (dictionary)* objects from SAP Signavio to the process step library of SAP Solution Manager objects.

[Mapping Attributes and Setting the Deletion Flag \[page 60\]](#)

Map recommended and customized attributes to be included within your synchronization scope.

[Previewing and Activating a Synchronization Project \[page 64\]](#)

Use the synchronization projects wizard's *Summary* page to view settings of your synchronization project and prompt it to start a synchronization run.

6.1 Creating a Synchronization Project

Learn how to create a synchronization project for each SAP Signavio Process Manager workspace and SAP Solution Manager solution that are to be synchronized together.

Context

A new synchronization project is required for the following scenarios:

- Synchronizing SAP Signavio workspace --> SAP Solution Manager solution.
- Synchronizing SAP Solution Manager solution --> SAP Signavio workspace.
- Synchronizing a once-synchronized SAP Signavio workspace --> an additional SAP Solution Manager solution.

Procedure

1. Launch the business process model connector for SAP Signavio solutions application.
2. From the main menu, select [Synchronization Projects](#).

The list of synchronization projects opens.

3. Choose [Add Sync Project](#).

The synchronization projects wizard opens at the [Define settings](#) stage.

4. Fill in required fields, making sure to follow the [Required systems](#) parameters.

Note

- For [SAP Signavio root folder](#), **Shared Documents** and next level down folders can be used in synchronization.
- For [SAP Solution Manager root folder](#), **Business Process** and next level down folders can be used in synchronization.

5. Confirm with [Include](#).

Results

The synchronization project is created and the wizard advances to the [Map Dictionary](#) stage.

Task overview: [Configure \[page 54\]](#)

Related Information

[Editing a Synchronization Project \[page 56\]](#)

[Mapping Objects \[page 58\]](#)

[Mapping Attributes and Setting the Deletion Flag \[page 60\]](#)

[Previewing and Activating a Synchronization Project \[page 64\]](#)

6.1.1 Synchronization Test Scenarios

See example scenarios for testing data sets in SAP Signavio --> SAP Solution Manager synchronization and SAP Solution Manager --> SAP Signavio synchronization.

If you are testing multiple data sets in synchronization scenarios:

- After a synchronization cycle finishes, use a separate project.
- Use a new set of data for testing scenarios.

Synchronization Direction: SAP Signavio --> SAP Solution Manager

Test Data Set 1 - Synchronization Project 1

- Scenario 1: Initial import SAP Signavio to SAP Solution Manager.
- Action 1: Change data in SAP Signavio.
- Scenario 2: Update synchronization run of SAP Signavio to SAP Solution Manager.
- Action 2: Change data in SAP Signavio.
- Scenario 3: Update synchronization run of SAP Signavio to SAP Solution Manager.
- Action 3: Change data in SAP Signavio.

Synchronization Direction: SAP Solution Manager --> SAP Signavio

Test Data Set 1 (or alternative) - Synchronization Project 2

📘 Note

To test a new data set or the same data set 1 as in SAP Signavio --> SAP Solution Manager synchronization testing, set up a separate synchronization project.

- Scenario 1: Initial import SAP Solution Manager to SAP Signavio.
- Action 1: Change data in SAP Signavio.
- Scenario 2: Update synchronization run of SAP Solution Manager to SAP Signavio.
- Action 2: Change data in SAP Signavio.
- Scenario 3: Update synchronization run of SAP Solution Manager to SAP Signavio.
- Action 3: Change data in SAP Signavio.

📘 Note

If an additional data set requires testing where the **top root folder** or **mapped dictionary category** differs from the previous synchronization project, set up a new project to test it.

6.2 Editing a Synchronization Project

Learn how to make changes to your synchronization project and avoid synchronization run errors.

Prerequisites

You created a synchronization project with the business process model connector for SAP Signavio solutions.

Procedure

1. From the main menu of the business process model connector for SAP Signavio solutions, select [Synchronization Projects](#).

The list of synchronization projects opens.

2. Select the project you want to edit and choose [Edit](#).

The synchronization projects wizard opens at the [Define settings](#) stage.

3. Add changes to the fields as needed.

Note

To avoid errors with the synchronization run, make changes at the [Map Attributes](#) stage only.

Changing the following project settings can cause the run to fail:

- Name
- Description
- Required systems
- Mapping of dictionary settings

Task overview: [Configure \[page 54\]](#)

Related Information

[Creating a Synchronization Project \[page 54\]](#)

[Mapping Objects \[page 58\]](#)

[Mapping Attributes and Setting the Deletion Flag \[page 60\]](#)

[Previewing and Activating a Synchronization Project \[page 64\]](#)

6.2.1 Pin Synchronization Projects for Later Editing

You may identify some synchronization projects as essential and potentially needing adjustments during productive synchronization or after initial synchronization. Use the pin feature to quickly access these projects from the project list.

Once you create and save a synchronization project, it is added to the [Sync Project List](#) within the connector interface. If you work with multiple projects, pinning a project moves it to the top of the list, allowing for enhanced visibility and easy access.

To pin a project, launch the connector, navigate to [Synchronization Projects](#) [Sync Project List](#), and select [★ \(pin\)](#) next to the project name.

Note

Pin settings save locally on your machine or in your browser cache. These settings don't carry over to different user sessions. If you switch devices or browsers, you'll need to re-pin your essential projects.

6.3 Mapping Objects

Learn how to map *activity (dictionary)* objects from SAP Signavio to the process step library of SAP Solution Manager objects.

Prerequisites

You completed the *Define settings* stage in the synchronization projects wizard.

Context

In the *Map Dictionary* stage, the connector proposes object mappings for all the available *activity (dictionary)* categories or sub-categories in the SAP Signavio dictionary mapping field. You can review the results table and select the required category or sub-category (activity).

Procedure

1. From the *Map Dictionary* stage, select the mapping field and start to enter the name of *activity (dictionary)* to be mapped. Check the proposed dictionary categories and sub-categories, and select the required entry.
 - If the entry already exists in the SAP Signavio Process Manager dictionary, choose it from the drop-down list of suggested entries.
 - If the required category (activity) does not exist in the SAP Signavio Process Manager dictionary, enter the full name of the category and select *Enter* instead of choosing one of the suggested entries.

Note

Only *activity (dictionary)* categories or sub-categories are displayed in the dictionary mapping field for activities. In SAP Signavio, if the main category is *activity (dictionary)*, its sub-categories can be set up as a different type to the main category. In this case, the sub-categories are not visible in the connector dictionary mapping for activities.

The connector saves the new entry. During synchronization, the connector creates the required *activity (dictionary)* category in SAP Signavio.

2. If you need to change the dictionary category, type the new category name in the *Proposed dictionary category* field.

- If the entry with the updated name already exists in the SAP Signavio Process Manager dictionary, choose it from the drop-down list.

ⓘ Note

If *activity (dictionary)* was renamed in SAP Signavio, you need to manually update the synchronization project to map the new name of the *activity (dictionary)* to keep the changes consistent. You can select the new name of *activity (dictionary)* and update it in the *Proposed dictionary category* field. By typing the new name in the field, the name is visible and can be selected.

3. When mapping is complete, confirm with *Include*.

Results

The synchronization projects wizard advances to the *Map Attributes* stage.

ⓘ Note

After the *Map Attributes* stage and after you run a synchronization, you can find the same objects in both your SAP Signavio Process Manager dictionary and the SAP Solution Manager library if the following conditions are met:

- The objects are required for synchronization.
- The objects are used in process models or processes of the process structure.

🔗 Example

Proposed dictionary category	Dictionary category type	Object type	Area
SAP Process Steps	Activity	Process Step	Process Step Library

- The table's *Proposed dictionary category* and *Dictionary category type* columns represent objects from SAP Signavio Process Manager.
- The table's *Object type* and *Area* columns define objects from SAP Solution Manager.

Task overview: [Configure \[page 54\]](#)

Related Information

[Creating a Synchronization Project \[page 54\]](#)

[Editing a Synchronization Project \[page 56\]](#)

[Mapping Attributes and Setting the Deletion Flag \[page 60\]](#)

[Previewing and Activating a Synchronization Project \[page 64\]](#)

6.4 Mapping Attributes and Setting the Deletion Flag

Map recommended and customized attributes to be included within your synchronization scope.

Prerequisites

- You completed the [Map Dictionary](#) stage in the synchronization projects wizard.
- Any attributes to be mapped already exist in SAP Signavio and SAP Solution Manager systems.

Context

In the [Map Attributes](#) stage, the business process model connector for SAP Signavio solutions supports mappings for SAP Signavio and SAP Solution Manager attributes. You can review the results table and accept the suggestions or customize your own attributes.

In this stage, you also set the conditions for synchronization of deleted tasks, [activity \(dictionary\)](#) objects, links to SAP Signavio objects, and Variant Management information. Setting these conditions is optional. If required, set conditions to indicate and synchronize changes and additional process information to SAP Solution Manager.

Procedure

1. From the [Map Attributes](#) stage, navigate to the [Recommended](#) tab and check the proposed attributes and other optional conditions for mapping.

3. Map Attributes

Define attributes to be included in the synchronization project. Please ensure that only attributes with supported data types are selected for mapping, and selected attributes have the same data types in both SAP Signavio and SAP Solution Manager systems.

Recommended | Customized

Recommended attributes are optional and can be included if required.

Process Manager Attribute	Source	Solution Manager Attribute	Used in
☐ Documentation	SPM Task	Description	SAP_SIGNAVIO PMDC
☐ Task Type	Task	Task Type	SAP_SIGNAVIO

SAP Signavio Process Manager

Define other SAP Signavio Process Manager attributes

Selectable assignment to Task and Activity

Select SAP Signavio Process Manager attribute

Process Manager Attribute (Dictionary and Task)

SAP Solution Manager

Define other SAP Solution Manager attributes

Select SAP Solution Manager custom attribute

Solution Manager Attribute (Dictionary)

Link to SAP Signavio objects

Solution Manager Attribute (Task)

2. If no changes need to be made, proceed with [Step 4](#).
3. If you need to customize attributes, choose the [Customized](#) tab.
 - a. Type the new attribute name in the [Select SAP Signavio custom attribute](#) field.
 - b. Choose the name from the drop-down list's suggested entries and select [Add attribute](#).

Note

Here you can add a customized attribute to a process.

- For a process template, set the custom attribute to [Process Template](#).
- For a process variant, set the custom attribute to [Process Variant](#).
- For an independent or standalone process, set the custom attribute to [No Variant Management](#).

4. Optional: Under [Deletion Flag](#), choose the Boolean type attribute that will be used in SAP Solution Manager to flag objects for deletion in SAP Solution Manager.

The same SAP Solution Manager attribute is used to flag both [task](#) and [activity \(dictionary\)](#) objects for deletion. As a prerequisite, the corresponding [task](#) or [activity \(dictionary\)](#) objects have been deleted in SAP Signavio.


Note

After the [Deletion Flag](#) is mapped, it becomes a mandatory attribute.

The [Deletion Flag](#) attribute is also changeable. If needed, you can replace it with a different Boolean attribute.

5. Optional: Under [Link to SAP Signavio object](#), choose the text type attribute to be used in SAP Solution Manager to pass the URL information in text format to SAP Solution Manager.
6. Optional: Under [Variant Management \(Process Template / Process Variant\)](#), choose the text type attribute to be used in SAP Solution Manager to indicate if a synchronized process belongs to Variant Management.
7. When mapping for the entire results table is complete and all optional conditions are set, confirm with [Include](#).
 - The [process step \(reference\)](#) or [process step \(original\)](#) will be flagged for deletion with an active Boolean attribute if a [task](#) or [activity \(dictionary\)](#) object is deleted in SAP Signavio and changes are synchronized to SAP Solution Manager.

Example



- The corresponding object, [process step \(reference\)](#) or [process step \(original\)](#) in SAP Solution Manager, is not deleted after an update synchronization from SAP Signavio to SAP Solution Manager. You must manually delete objects that are flagged for deletion in SAP Solution Manager.

- After synchronization is complete in SAP Solution Manager, the Boolean attribute used to flag *process step (reference)* or *process step (original)* objects for deletion is shown as active.

Note

All attributes and artifacts assigned to the *process step (reference)* or *process step (original)* must be reviewed and validated for deletion or archiving before the object can be manually deleted in SAP Solution Manager.

If you delete a *process step (reference)* or *process step (original)* in SAP Solution Manager, you delete all artifacts that have been attached to those objects.

A link to an SAP Signavio object in SAP Signavio Process Collaboration Hub is visible in SAP Solution Manager in text format if this option is included in the sync project mapping. The following objects are updated with the link in SAP Solution Manager after synchronization from SAP Signavio to SAP Solution Manager:

- Folders
- Scenarios

Variant Management information is visible for every process in SAP Solution Manager if this option is included in the sync project mapping. The process is flagged as one of the following:

- Process variant
- Process template
- No Variant Management

Task overview: [Configure \[page 54\]](#)

Related Information

[Creating a Synchronization Project \[page 54\]](#)

[Editing a Synchronization Project \[page 56\]](#)

[Mapping Objects \[page 58\]](#)

[Previewing and Activating a Synchronization Project \[page 64\]](#)

Adding a Deletion Flag During an Active Synchronization Project

Context

The following steps apply if you have an existing active synchronization project and need to add a deletion flag attribute.

Procedure

1. Navigate to the business process model connector for SAP Signavio solutions entry screen.
2. Choose the [Synchronization projects](#) tile.
3. Select your synchronization project name from the list.
The project opens in editable mode.
4. Navigate to the [Map Attributes](#) stage.
5. Under [Deletion Flag](#), choose the Boolean type attribute that will be used to flag objects for deletion in SAP Solution Manager.
6. When mapping for the entire results table is complete and the deletion flag set, confirm with [Include](#).

6.4.1 Deletion Flag Functionality

Learn how the deletion flag works with different objects when mapping between SAP Signavio and SAP Solution Manager systems.

The following chart shows the relationship between a deletion action taken in SAP Signavio and the deletion flag imported to SAP Solution Manager. For more information about the deletion flag, see [Mapping Attributes and Setting the Deletion Flag \[page 60\]](#).

Action in SAP Signavio	SAP Signavio Object	SAP Solution Manager Object	SAP Solution Manager Object Flagged for Deletion
Task , which is linked to Activity (Dictionary) , is deleted in a BPMN Model.	Task	Process Step (reference)	Process Step (reference)
Task , which is not linked to Activity (Dictionary) , is deleted in a BPMN Model.	Task	None.	None

Note

Tasks that are not in [Activity \(Dictionary\)](#) mapped in Sync Project are skipped during synchronization to SAP Solution Manager and a warning log message is displayed.

Action in SAP Signavio	SAP Signavio Object	SAP Solution Manager Object	SAP Solution Manager Object Flagged for Deletion
Activity (Dictionary) used in a BPMN Model.	Activity (Dictionary)	Process Step (original)	Process Step (original)
 Note if Activity (Dictionary) is deleted, then the model Task that was linked to it before deletion is not linked to the Activity (Dictionary). The Task will be skipped in synchronization, unless you link it to a different Activity (Dictionary) before synchronizing the updates.			
Activity (Dictionary) is not used in a BPMN Model.	Activity (Dictionary)	Process Step (original)	Process Step (original)

6.4.2 Reverted Deleted Tasks

If you restore the model and revert deleted tasks in SAP Signavio, then the following SAP Solution Manager deletion flag conditions apply:

- If the corresponding [process step \(reference\)](#) is still available and visible in the process structure, the deletion flag is removed from the [process step \(reference\)](#) after the restored SAP Signavio model is synchronized to SAP Solution Manager.
- If the corresponding [process step \(reference\)](#) is deleted from SAP Solution Manager, then the restored task is re-imported from SAP Signavio as a new [process step \(reference\)](#) with a new [process step \(reference\) ID](#). Any previously-assigned artefacts such as documentation, transaction, or test cases need to be re-assigned to the new [process step \(reference\)](#).

6.5 Previewing and Activating a Synchronization Project

Use the synchronization projects wizard's [Summary](#) page to view settings of your synchronization project and prompt it to start a synchronization run.

Prerequisites

You completed the [Map Attributes](#) stage in the synchronization projects wizard.

Context

- An active project is ready for synchronization.
- An inactive project can have settings changed or can be deleted.

Procedure

1. From the [Summary](#) page, check the settings for the selected synchronization project, which is currently open to show details.
2. To activate the project, choose [Activate](#).

You navigate to the [Synchronizations Projects](#) page, where you can see the [Active](#) status attached to your selected synchronization project, along with a list of your other active and inactive synchronization projects.

3. To keep the project inactive, choose [List sync projects](#).

You navigate to the [Synchronizations Projects](#) page, where you can view all your active and inactive synchronization projects.

Task overview: [Configure \[page 54\]](#)

Related Information

[Creating a Synchronization Project \[page 54\]](#)

[Editing a Synchronization Project \[page 56\]](#)

[Mapping Objects \[page 58\]](#)

[Mapping Attributes and Setting the Deletion Flag \[page 60\]](#)

7 Run

This stage of the workflow carries out synchronizations.

Executing a synchronization requires an **active** synchronization project. Once activated, a project can be run.

📘 Note

Before running synchronization, we recommend becoming familiar with various synchronization approaches and recommended synchronization methodology described in [Integration of SAP Signavio Process Manager with SAP Solution Manager 7.2 \(PDF\)](#).

[Activating a Synchronization Project \[page 66\]](#)

Enable synchronizations to be run by activating a synchronization project.

[Running a Synchronization \[page 67\]](#)

Learn how to synchronize content between SAP Signavio Process Manager and SAP Solution Manager.

7.1 Activating a Synchronization Project

Enable synchronizations to be run by activating a synchronization project.

Context

A synchronization project must be activated before it can be executed and used in synchronization run. Activation creates the required dictionaries and attributes in SAP Signavio Process Manager.

Procedure


1. Launch the connector application.
2. From the main menu, select [Synchronization Projects](#).
3. Locate the project you wish to activate and click on its ellipses menu.
4. Select [Activate](#).

Activation begins. This may take several minutes as SAP Signavio settings are checked and the dictionaries and attributes are created.

📘 Note

You can verify that all mandatory attributes and dictionaries have been created according to the synchronization project's specifications in the relevant SAP Signavio

workspace. Check the *Attributes* and *Dictionary* categories in *Define notations/attributes*.



Task overview: [Run \[page 66\]](#)

Related Information

[Running a Synchronization \[page 67\]](#)

7.2 Running a Synchronization

Learn how to synchronize content between SAP Signavio Process Manager and SAP Solution Manager.

Context

Establish the primary system when you specify the direction in which you plan to sync data:

- SAP Signavio Process Manager to SAP Solution Manager, where SAP Solution Manager receives and integrates content from SAP Signavio Process Manager.
- SAP Solution Manager to SAP Signavio Process Manager, where SAP Signavio Process Manager receives and integrates content from SAP Solution Manager.


Specifying the synchronization direction automatically controls the selection of content to be synchronized.

Note

Synchronization of objects from SAP Solution Manager to SAP Signavio should be used for the initial import of process content only. An update synchronization from SAP Solution Manager to SAP Signavio is not supported and may result in an error. For more information about synchronization best practices and various approaches that might be applied, see [Integration of SAP Signavio Process Manager with SAP Solution Manager 7.2 \(PDF\)](#).


Procedure

1. Launch the connector application.
2. Choose the *Run Synchronization Projects* tile.
The *Synchronization Projects* window opens.
3. From the list of synchronization projects, navigate to your project's row.
4. At the end of the row, choose  (*more options*) and select *Run sync project*.



The *Define settings* window opens atop the project window.

5. Specify the synchronization direction.



6. Optional: Use the dropdown fields to change the preselected project and system names, if needed.
7. Confirm with *Start*.

Results

The synchronization is executed in stages. Leave the project window open to track the progress of each stage.

Next Steps

Optional: Confirm the synchronization status under the *Summary* page's *Sync history* tab.

A successful synchronization displays a *Completed* status. Select this status to view detailed logs.

Note

If your synchronization project does not advance past the *in progress* status, select the status to open the project, where you can choose *Cancel sync* from the header area.

Example

Status	Step	Message	Start	End
Completed	Sync initialization	Validate Sync project data	11/12/2024, 14:06:24	11/12/2024, 14:06:24
Completed	Sync initialization	Enrich Sync Run Parameters	11/12/2024, 14:06:25	11/12/2024, 14:06:25
Completed	Sync initialization	Validate Active Sync - Parallel sync for this project already in progress	11/12/2024, 14:06:25	11/12/2024, 14:06:25
Completed	Sync initialization	Initialize Controller Steps	11/12/2024, 14:06:25	11/12/2024, 14:06:25
InProgress	Sync initialization	Create Signavio and Solman Object Mapping	11/12/2024, 14:06:25	

Cancelling a synchronization stops progress at a project's current synchronization phase. It does not revert successful synchronization up to that point. The project does not begin synchronization at the next phase.

Task overview: [Run \[page 66\]](#)

Related Information

[Activating a Synchronization Project \[page 66\]](#)

8 System Settings

Configure system settings that need to be applied centrally to the whole connector application.

The new system settings functionality are implemented for data protection and removes synchronization logs automatically. The settings are not user-specific and are applied at the system level, which effects capabilities of the connector centrally and independently from the user preferences.

By default, logs older than 90 days will be removed. Review this value in the System Settings tile and adjust it to meet your needs.

📘 Note

Only users who are assigned either the *Full Admin* or *Project Admin* role collection in the connector application can access system settings functionality.

To learn how to configure data retention rules for synchronization logs, see [Setting the Synchronization Log Retention Period \[page 78\]](#).

9 Monitor

Learn how to access the log history.

Accessing the Log History

To access the synchronization run history for a project, follow these steps:

1. Open the [Synchronization Projects](#) tile from the front screen.
2. Next to the project, click the ellipses for more options and choose [Sync History](#).
A list appears, displaying the sync runs that have been created for your sync projects so far.
3. From the list, click on the sync run log you wish to view.
This brings up the synchronization log viewing page, where you can navigate to all messages from each of the sync phases and steps.
4. Click on the phase or step you wish to review.
Alternatively, open up the sync project definition. Next to the project you want to explore, click the ellipses for more options and click the synchronization run log you wish to view.

Choose a phase and a step to view logs associated with your project, and select the [Sync History](#) tab.

9.1 Synchronization History

Learn how to access your sync history to monitor sync runs and sync projects.

From the [Synchronization Projects](#) window, find your sync project's row within the list of synchronization

projects, choose  ([more options](#)), and select [Sync History](#).

[Sync History](#) is accessed from your sync project summary page.

Select the [Sync History](#) tab to view the following project details:

- **Status:** A successful sync shows a [Completed](#) status. Other end statuses are [Canceled](#) and [Failed](#).
- **Sync direction:** Shows which system pushed updates to which system. *SIG* stands for SAP Signavio and *SOL* stands for SAP Solution Manager. *SOL Executables* stands for import of executables from SAP Solution Manager to SAP Signavio.
- **Sync Run ID:** The ID to represent the sync. Each sync has its own ID.
- **Last run by:** The email address of the user who initiated the sync.
- **Sync run at:** Timestamp of the sync.
- **Logs:** You can download the logs for the sync run by selecting [Download](#). The file is saved to your local downloads folder as an MS Excel file.

Example

Sync history					
Status	Sync direction	Sync run ID	Last run by	Sync run at	Download Logs
Completed	SOL Executables	1e7f89a6-28ab-4ba8-876c-0bc680114521	User ID	20/01/2025, 10:15:56	Download
Completed	SIG > SOL	95921cf-84f8-4b0e-aacb-04cd70cd119d	User ID	20/01/2025, 10:18:10	Download
Completed	SOL > SIG	#5fab8c-92cb-4bdf-a3e4-eab779442619	User ID	20/01/2025, 10:13:11	Download

Related Information

[Running a Synchronization \[page 67\]](#)

10 Security Guide

The Security Guide describes matters concerning user access control, synchronization logs, and data security.

[Creating Users \[page 73\]](#)

Set up a user's access by adding their credentials.

[Assigning Roles \[page 74\]](#)

Manage user access by assigning the user one or more roles.

[Audit Logs \[page 76\]](#)

Learn more about audit logs generated for your tenant of the business process model connector for SAP Signavio solutions.

[Setting the Synchronization Log Retention Period \[page 78\]](#)

Learn how to define data retention rules and permanently delete personal data from the connector application.

[Data Security \[page 80\]](#)

When subscribing to a multi-tenant application, it is important to understand the security of your data.

[Advanced IP-Based Security \[page 81\]](#)

Learn how, by accessing and using the business process model connector for SAP Signavio solutions, you can securely connect your SAP Solution Manager system in your data center during synchronization.

10.1 Creating Users

Set up a user's access by adding their credentials.

Prerequisites

User access to the application is managed by the User Authentication & Administration (XSUAA) service. Access management should only be done once you have subscribed to the application.

Context

When you subscribed to the application, it was deployed to use a subaccount. A user is created by adding their email address to this subaccount.

Procedure

1. Open **SAP BTP Cockpit**.
2. From the sidebar, select ► [Security](#) ► [Users](#) ► [Create](#) ►.
3. Enter the new user's email and choose [OK](#).

Results

The new user is added. You can now proceed to assigning them a role.

Task overview: [Security Guide \[page 73\]](#)

Related Information

[Assigning Roles \[page 74\]](#)

[Audit Logs \[page 76\]](#)

[Setting the Synchronization Log Retention Period \[page 78\]](#)

[Data Security \[page 80\]](#)

[Advanced IP-Based Security \[page 81\]](#)

[Subscribing to the Connector Application \[page 12\]](#)

10.2 Assigning Roles

Manage user access by assigning the user one or more roles.

Context

Different roles correspond to different levels of access. The following roles are available:

Role name	Level of access
Full Admin	Complete application functionality
System Creation	System creation and maintenance functions only
Project Admin	• Full access to synchronization projects and synchronization run functions • Read only access to systems

Role name	Level of access
Sync Run Admin	• Display access to systems • Change access to projects • Full permissions for synchronization runs
Display All	Display access to all functions within the application

A user should be assigned at least one role. A user can have multiple roles.

Note

Role: Provides a single authorization within a BTP application or service.

Role collection: Contains multiple roles, with each role representing a single authorization. Together, all roles in the collection provide the total authorizations a user needs to perform their job within a BTP application or service.

Caution

The business process model connector for SAP Signavio solutions supports the use of the standard-delivered role collections only, such as the following:

- *DisplayAll*
- *FullAdmin*
- *Project Admin*
- *SyncRunAdmin*
- *SystemAdmin*

Copying and assigning alternate role collections triggers the following error message: You do not have the right roles to access the connector launchpad.

Procedure

1. Open SAP BTP Cockpit.
2. Choose ► **Security** ► **Users** ▾ from the side panel.
3. Select a user.
4. Select the role needed and choose *Assign Role Collection*.

Results

The user is assigned their new role.

Task overview: [Security Guide \[page 73\]](#)

Related Information

[Creating Users \[page 73\]](#)

[Audit Logs \[page 76\]](#)

[Setting the Synchronization Log Retention Period \[page 78\]](#)

[Data Security \[page 80\]](#)

[Advanced IP-Based Security \[page 81\]](#)

10.3 Audit Logs

Learn more about audit logs generated for your tenant of the business process model connector for SAP Signavio solutions.

Logs are essential to monitor the security of your system and to track events for technical or administrative issues. For general information on all SAP Business Technology Platform audit logs, see [Audit Logging in the Cloud Foundry Environment](#).

In particular, the business process model connector for SAP Signavio solutions writes log entries for changes to system security and configuration, as shown in the following tables.

Note

Headings for both tables are defined as follows:

- **Trigger:** The event that takes place in the system which starts an automatic log entry generation.
- **Description:** Details regarding what the event is and what is logged when the event is triggered.
- **Identify As:** The key words to identify related log entries in an audit log.

Security events generating written audit logs (audit.security-events)

Trigger	Description	Identify As
Unauthorized request detected	User is missing an authorization when accessing a resource, such as a system configuration or a sync project configuration.	Unauthorized request detected in <Service Name> service
Credentials added to a system definition	A username and password are provided by the user when creating or editing a system definition.	System user and password created for object type system with ID <id> and name <name> by user <email>
Credentials deleted from a system definition	A username and password are replaced or removed by the user when editing or deleting the system definition.	System user and password deleted for object type System with ID <id> and name <name> by user <email>
Data modified	An update is made to the <i>synchronization log data retention period</i> in system settings.	Sync log retention parameter with ID <id> was updated to <newValue> by user <email>

Trigger	Description	Identify As
Sync log deleted	Each run ID is logged as deleted when sync run logs are deleted daily by an internal process.	Sync run logs with ID <id> have been deleted
Sync run created	Details of a sync run when a sync is triggered to run.	New sync run created with ID <id> and status <status> by user <email>
Sync run status changed	The status when a sync run changes its status.	Sync run with ID <id> has changed status to <status>
Sync run deleted	A sync run record is deleted as part of a daily removal of sync logs.	Sync run with ID <id> has been deleted by user <email>

Configuration change events generating written audit logs (audit.configuration)

Trigger	Description	Identify As
Connected system or synchronization project created	All new field values when a new system or sync project is created.	Configuration created for <objectType> with ID <id> and name <name> by user <email>
Connected system or synchronization project changed	All old and new field values when a system or sync project is changed.	Configuration updated for <objectType> with ID <id> and name <name> by user <email>
Connected system or synchronization project deleted	All old field values when a system or sync project is deleted.	Configuration deleted for <objectType> with ID <id> and name <name> by user <email>

Parent topic: [Security Guide \[page 73\]](#)

Related Information

[Creating Users \[page 73\]](#)

[Assigning Roles \[page 74\]](#)

[Setting the Synchronization Log Retention Period \[page 78\]](#)

[Data Security \[page 80\]](#)

[Advanced IP-Based Security \[page 81\]](#)

10.4 Setting the Synchronization Log Retention Period

Learn how to define data retention rules and permanently delete personal data from the connector application.

Prerequisites

You are assigned either the [Full Admin](#) or [Project Admin](#) role collection in the connector application where you want to access system settings.

Context

Running synchronizations within the application generates logs. The logs display timestamps and records of what has been created, changed, or deleted during each run. Also, logs show whether the synchronization completed successfully for each stage and object. Logs record the email addresses of users initializing the synchronizations.

Logs need to be purged from the system for the following reasons:

- Removal of personal identifiable information (PII), such as a user's email address, to comply with data privacy standards. Align your data purging strategies with your business and legal requirements.
- Maintenance of optimal application performance over time. Connector logs records are sensitive to high-growth rate which can quickly generate substantial volumes of data which might be impacting connector application performance.

When you set data retention rules, you trigger the data purging mechanism in the connector application to delete inactive or obsolete records from the connector logs permanently. Log deletion is triggered for all log types, successful and failed synchronization runs, once every 24 hours. The system calculates the logs of all synchronization runs that stopped prior to the retention period set in the [System Settings](#).

ⓘ Note

Deleted logs for each synchronization project are no longer visible in the [Synchronization History](#) list view for the project.

Procedure

1. From the main menu, choose the [System Settings](#) tile.

System settings

Data Protection and Privacy

Define data retention rules and permanently delete personal data from the connector application as required by your data purge standards.

Please select the amount of days for retaining synchronisation logs, until automatic deletion takes place.
Choose between a minimum of 10 and maximum of 180 days.

Amount of days: *

— 90 +

i Please note that data retention rules will trigger data purging mechanism in the connector application to permanently delete inactive or obsolete records from the connector logs. You must consider that connector logs records are sensitive to high-growth rate which can quickly generate substantial volumes of data that might be impactful connector application performance. We advise to align your data purging strategies with your business and legal requirements and only keep the logs data required by your data purge standards.

2. Navigate to the *Amount of days* field and adjust the number by selecting (+) or (-).

i Note

- The system deletes logs within 24 hours after the retention period is reached.
- The default log retention period is 90 days.
- The minimum available log retention period is 10 days. The minimum time allows for you to submit and receive assistance on any potential support tickets related to a failed synchronization.
- The maximum available log retention period is 180 days in order to manage log data volume and to timely remove information subject to data protection.

3. Confirm with *Save*.

Task overview: [Security Guide \[page 73\]](#)

Related Information

[Creating Users \[page 73\]](#)

[Assigning Roles \[page 74\]](#)

[Audit Logs \[page 76\]](#)

[Data Security \[page 80\]](#)


[Advanced IP-Based Security \[page 81\]](#)

10.5 Data Security

When subscribing to a multi-tenant application, it is important to understand the security of your data.

System Landscape

The following diagram illustrates the architecture of the solution:



Customer Data

Customer configuration, project definition and log data are all held in a dedicated container in SAP HANA Cloud. This container is protected and regularly backed up. It is also separated from all other customers using a string of credentials unique to your container, which is linked to your tenant and accessed only by users you add to the application

System Credentials

The credentials you provide to access both your SAP Signavio Process Manager system and your SAP Solution Manager system are held only in the BTP Destination service attached to your tenant subaccount. Those credentials are not stored in the SAP HANA Cloud container. The BTP Destination service is a fully certified secure store and credentials are protected at all times.

This is kept within your control and separate from all other customers.

On-Premise System Access

Access to your on-premise/hosted SAP Solution Manager system is controlled by the Cloud Connector linked to the subaccount with which you subscribed.

All permissions are managed by you within the Cloud Connector. Only connections from your application tenant to your SAP Solution Manager system are allowed.

Parent topic: [Security Guide \[page 73\]](#)

Related Information

[Creating Users \[page 73\]](#)

[Assigning Roles \[page 74\]](#)

[Audit Logs \[page 76\]](#)


[Setting the Synchronization Log Retention Period \[page 78\]](#)

[Advanced IP-Based Security \[page 81\]](#)

10.6 Advanced IP-Based Security

Learn how, by accessing and using the business process model connector for SAP Signavio solutions, you can securely connect your SAP Solution Manager system in your data center during synchronization.

Security goal	Action required	Result
Increase the security of the connection to the SAP Solution Manager system.	Implement IP address restrictions on your SAP Cloud Connector, hosted in your data center. For the business process model connector for SAP Signavio solutions, add only the public IP addresses of the connectivity proxy used by the business process model connector for SAP Signavio solutions to reach your SAP Cloud Connector.	This restricts the IP addresses of the systems with which your SAP Cloud Connector can communicate to those used by the business process model connector for SAP Signavio solutions.



- [End User \[page 81\]](#)
- [End User \[page 81\]](#)
- [Customer Offices \[page 81\]](#)
- [Customer Data Center \[page 81\]](#)
- [Access using customer-specific URL \[page 81\]](#)
- [Authenticate and log on \[page 81\]](#)
- [Authentication Service \[page 81\]](#)
- [Customer Subscriber Subaccount \[page 81\]](#)
- [SAP Provider Subaccount \[page 81\]](#)
- [BPMC application \[page 81\]](#)
- [Cloud Connector \[page 81\]](#)
- [Authentication Service \[page 81\]](#)
- [Access via mTLS secured tunnel configured by customer from their Cloud Connector \[page 81\]](#)
- [SAP Solution Manager \[page 81\]](#)

Key

Acronym	Full Name
BPMC	business process model connector for SAP Signavio solutions
SAP BTP	SAP Business Technology Platform

The business process model connector for SAP Signavio solutions runs on SAP Business Technology Platform (SAP BTP) using the Kyma Runtime. This means it has dedicated IP addresses only on its ingress gateway within each SAP BTP region where it's available. These IP addresses are unique to this application and differ from addresses used by other applications running on SAP BTP.

Add the IP addresses in the following table to the [IP allow-list](#) on your SAP Cloud Connector. This limits the IP addresses that the connector can communicate with to those you specify.

BPMC SAP BTP Regions	Connectivity Proxy IP Addresses
Europe Frankfurt (EU10)	3.123.62.208 63.180.73.254 63.181.164.126
US Virginia East (US10)	18.211.231.223 18.235.112.101 52.70.180.42

For more information, see SAP Note [3736021](#), *Synchronization fails on the step 'Create Signavio and SolMan Object Mapping' without any error message*.

Parent topic: [Security Guide \[page 73\]](#)

Related Information

[Creating Users \[page 73\]](#)

[Assigning Roles \[page 74\]](#)

[Audit Logs \[page 76\]](#)

[Setting the Synchronization Log Retention Period \[page 78\]](#)

[Data Security \[page 80\]](#)

11 Troubleshooting

Find solutions to possible issues with establishing your SAP Signavio Process Manager to SAP Solution Manager connection.

Troubleshooting Tips

If the instructions for the problem areas below do not resolve your issue or if you need help with the instructions, request SAP Support assistance. For more information, see [Creating a Support Case \[page 88\]](#).

Problem Area	Instruction
Web dispatcher host header validation	Use a browser and run: <code>https://<myLoadbalancerServiceAddress.com>/sap/bc/bsp/sap/system_test/test_proxy.htm</code>
HTTP Error Code 401	• Check SSL client certificate is set as Optional. • Configure Alternative Logon Methods per SICF service.
HTTP Error Code 403 SICF service is not enabled.	In transaction SICF, an administrator must check the service <code>/sap/opu/odata/sap/ProcessManagement</code> and set it to active .
HTTP Error Code 500 • Target unable to determine further action with the request. • Possible configuration issue or software operational issue.	Double-check your configuration and retry your last action that they were doing.
SSL peer not trusted/verified	Check if there is a missing root chain or an invalid SSL SNI setup on the backend system.
No data found from SAP Solution Manager	Check the technical user and the roles in SAP Solution Manager. For more information, see Necessary user rights .
The synchronization project seems to have stalled. The project status under the Sync history tab does not change from in progress .	Consider canceling the synchronization, as described in Running a Synchronization [page 67] . Canceling a synchronization does not erase all progress. Instead, canceling stops progress at a project's current synchronization phase. Running a new synchronization continues where the canceled synchronization had stopped.

Primary Troubleshooting SAP Note

SAP Note Number	Title
3343311 	Troubleshooting Signavio BTP Connector to Solution Manager

Additional Troubleshooting SAP Notes

SAP Note Number	Title
2616927 	Troubleshooting for basic errors and configuration problems in WDP - Guided Answers
2394406 	Required information for analyzing SSL issues on Web Dispatchers
510007 	Additional considerations about setting up SSL on Application Server ABAP

Troubleshooting Checklists

SubAccount

General troubleshooting checklist:

- Subscribed to business process model connector for SAP Signavio solutions for SAP Signavio solutions.
- Completed IAS setup with or without role collection & Azure AD Group SAML claim mapping.

SAP Signavio application-specific subaccount checklist:

- Confirmed that you were assigned the full administrator rights during the initial setup.
- Confirmed that the SAP Solution Manager settings are as follows:
 - Host name = This is the internal load balancer name of the SAP Solution Manager system, or local ICM if no LB layer exists.
 - Port = The virtual port which is also to be specified as virtual port in the Cloud Connector.

Header			
System ID: DY1	Support Package Stack: Solman 7.2 SP013	Description: Solution Manager DY1	
System Type: SAP Solution Manager 7.2	Role: Development	Client Number: 001	
Technical info			
Host name: dy1-web[REDACTED].net	Port number: 443	Authentication type: Basic	Certificate type: Trusted
System creation log			
Destination: [X] SM-DY1-001-SCCDEV	Virtual URL: [X] dy1001.sccdev.virtual.domain	Location ID: SCCDEV	

Identity Authentication Service (IAS)

Troubleshooting checklist:

- Confirmed proper setup of IAS subaccount application for Azure authentication.
- Optional: Configured IAS application setup to allow Azure AD group mapping.

Cloud Connector

Troubleshooting checklist:

- Connected to the subaccount with/without location ID.
- Checked that system & UI certificate is not self-signed using PKI or approved SAP root CA.
- Created a virtual host entry identical to the value specified in the subaccount destination generated by SAP Signavio application to SAP Solution Manager system.
- Set host header to [Internal Host](#) to avoid [Host_header](#) mismatch on load balancer layer.
- Confirmed that X.509 principal propagation is not set for this entry.
- Cloud Connector version 2.13 and older: Set the principal propagation to [None](#), allowing basic authentication.
- Cloud Connector version 2.14x: Set the principal propagation to [Strict Usage](#) to avoid the local ICF modification.
- Cloud Connector version 2.15 and higher: Followed [SAP BTP Connectivity](#) instructions.

IP Load Balancer

Troubleshooting checklist:

- Confirmed that SSL service has a valid SSL certificate and is not self-signed using PKI or an approved SAP root CA.
- Confirmed that X.509 client certificate authentication is not set to [Mandatory](#) and as a result, allows basic authentication.

Web Dispatcher

Troubleshooting checklist:

- Confirmed that SSL service has a valid SSL certificate and is not self-signed using PKI or an approved SAP root CA.
- Checked that SSL trust towards SAP Solution Manager system is set up properly.
- Confirmed that X.509 client certificate authentication is not set to [Mandatory](#) and as a result, allows basic authentication to lower systems.

SAP Solution Manager

Troubleshooting checklist:

- Confirmed that the SSL service is signed by a root CA (internal PKI or an approved SAP root CA).
- Configured SICF services for SAP Signavio, if there is any SSO solution enabled (SPNEGO/Kerberos, SAML). Under the [Logon Data](#) tab, chose procedure as [Alternative Logon Procedure](#). Selected the option [Use all logon procedures](#).
- Checked that SSL trust works from load balancer layer with basic authentication for the SAP Signavio related services.

BTP to On-Premise: References and Guidance

Area	Documentation
BTP Global Account	Getting Started
BTP SubAccount Entitlements	Account Model
IAS and Custom IdP	Trust and Federation with Identity Providers
IAS Configuration Guide	Operation Guide
Cloud Connector	Cloud Connector
SSL Web Dispatcher	Configuring SAP Web Dispatcher to Support SSL

11.1 Troubleshooting - Creating a Subaccount

If you encounter issues related to an SAP Signavio Process Manager to SAP Solution Manager connection, check the steps for creating a subaccount.

Prerequisites

You have the [Global Account](#) administrator role.

Procedure

1. Navigate to SAP Business Technology Platform (SAP BTP) cockpit.
<https://emea.cockpit.btp.cloud.sap/cockpit/> 
2. Create subaccount in either EU10 or US10 on AWS.
3. Choose ► [Entitlements](#) ► [Entity Assignment](#) ► [Select your SubAccount](#) ►.
4. Configure new entitlement business process model connector for SAP Signavio solutions.

11.2 Creating a Support Case

Learn how to request SAP Support assistance, should you need help with the business process model connector for SAP Signavio solutions.

Context

In the event that you experience an issue when using the connector, follow these steps to reach out to SAP Support.

Procedure

1. Log on to [SAP for Me](#).

If you require access, locate a colleague in your organization who has access or can grant you access.

2. In the [Customer](#) section, provide the **S-user** and other details as prompted
3. In the [System Information](#) section, provide the [System](#) and [Product Area](#). Here, you can search for a system or select one of your recently-used systems from the dropdown list.
4. In the [Description](#) field, provide the following information:

Option	Description
Subject	Provide a title to summarize the problem.
Description	• Describe the issue with as much detail as possible. • Add steps taken before the issue occurred.
Category	If applicable, you can include BPI-SIG-CA-BMB, which is the component for Solution Manager Service by SAP Signavio.
Attachments	Add screenshots showing the issue or error message.

5. Provide contact and priority information.
6. Choose [Review & Submit Incident](#).

SAP Support processes the submission and contacts you to diagnose and resolve the issue.

11.3 Built-In Support

Learn how to get real-time support and find context-sensitive information from within business process model connector for SAP Signavio solutions.

Built-In Support provides simplified guided support that allows you to search for knowledge directly within the application.

When you're signed in, you can open the Built-In Support panel by choosing  (*Built-In Support*) at the top right of the screen. Enter one or more key words and choose from the results displayed in the right-side panel. Filter the results by selecting  (*filter*).

Important Disclaimers and Legal Information

Hyperlinks

Some links are classified by an icon and/or a mouseover text. These links provide additional information.

About the icons:

- Links with the icon  : You are entering a Web site that is not hosted by SAP. By using such links, you agree (unless expressly stated otherwise in your agreements with SAP) to this:
 - The content of the linked-to site is not SAP documentation. You may not infer any product claims against SAP based on this information.
 - SAP does not agree or disagree with the content on the linked-to site, nor does SAP warrant the availability and correctness. SAP shall not be liable for any damages caused by the use of such content unless damages have been caused by SAP's gross negligence or willful misconduct.
- Links with the icon  : You are leaving the documentation for that particular SAP product or service and are entering an SAP-hosted Web site. By using such links, you agree that (unless expressly stated otherwise in your agreements with SAP) you may not infer any product claims against SAP based on this information.

Videos Hosted on External Platforms

Some videos may point to third-party video hosting platforms. SAP cannot guarantee the future availability of videos stored on these platforms. Furthermore, any advertisements or other content hosted on these platforms (for example, suggested videos or by navigating to other videos hosted on the same site), are not within the control or responsibility of SAP.

Beta and Other Experimental Features

Experimental features are not part of the officially delivered scope that SAP guarantees for future releases. This means that experimental features may be changed by SAP at any time for any reason without notice. Experimental features are not for productive use. You may not demonstrate, test, examine, evaluate or otherwise use the experimental features in a live operating environment or with data that has not been sufficiently backed up.

The purpose of experimental features is to get feedback early on, allowing customers and partners to influence the future product accordingly. By providing your feedback (e.g. in the SAP Community), you accept that intellectual property rights of the contributions or derivative works shall remain the exclusive property of SAP.

Example Code

Any software coding and/or code snippets are examples. They are not for productive use. The example code is only intended to better explain and visualize the syntax and phrasing rules. SAP does not warrant the correctness and completeness of the example code. SAP shall not be liable for errors or damages caused by the use of example code unless damages have been caused by SAP's gross negligence or willful misconduct.

Bias-Free Language

SAP supports a culture of diversity and inclusion. Whenever possible, we use unbiased language in our documentation to refer to people of all cultures, ethnicities, genders, and abilities.

© 2026 SAP SE or an SAP affiliate company. All rights reserved.

No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company. The information contained herein may be changed without prior notice.

Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other countries. All other product and service names mentioned are the trademarks of their respective companies.

Please see <https://www.sap.com/about/legal/trademark.html> for additional trademark information and notices.

