TP ASTERISK

VM Server asterisk

- → En NAT
- → Edit > Virtual Network Editor > VMnet8 > Change Settings > Décocher DHCP

Installation IVR

- apt update
- apt upgrade
- apt install perl
- apt install libwww-perl
- apt install sox
- apt install mpg123
- apt install flac

Téléchargement de « googletts.agi »

- cd /var/lib/asterisk/agi-bin
- wget -4 https://raw.github.com/zaf/asterisk-googletts/master/googletts.agi
- chmod +x googletts.agi
- asterisk -rvvv
- module show

Configuration SIP

->/etc/asterisk/sip.conf - nano /etc/asterisk/sip.conf [general] language=fr bindaddr=0.0.0.0 dtmfmode=rfc2833 disallow=all allow=ulaw allow=alaw hassip=yes hasiax=no callwaiting=yes transfer=yes canpark=yes hasvoicemail=yes deny=0.0.0.0/0.0.0.0 permit=192.168.75.0/255.255.255.0 qualify=yes ; Utilisateurs Administration [300] secret=1234 callerid="Admin1" <300> mailbox=300@default voicemail.conf type=friend host=dynamic nat=no context=administration

- cp /etc/asterisk/sip.conf /etc/asterisk/sip.conf.original

```
[301]
secret=1234
callerid="Admin2" <301>
mailbox=301@default
voicemail.conf
type=friend
host=dynamic
nat=no
context=administration
[302]
secret=1234
callerid="Admin3" <302>
mailbox=302@default
voicemail.conf
type=friend
host=dynamic
nat=no
context=administration
; Utilisateurs Comptabilité
[400]
secret=1234
callerid="Compta1" <400>
mailbox=400@default
voicemail.conf
type=friend
host=dynamic
nat=no
context=comptabilite
```

```
secret=1234
callerid="Compta2" <401>
mailbox=401@default
voicemail.conf
type=friend
host=dynamic
nat=no
context=comptabilite
[402]
secret=1234
callerid="Compta3" <402>
mailbox=402@default
voicemail.conf
type=friend
host=dynamic
nat=no
context=comptabilite
; Utilisateurs Mécanique
[500]
secret=1234
callerid="Meca1" <500>
mailbox=500@default
voicemail.conf
type=friend
host=dynamic
nat=no
context=mecanique
[501]
secret=1234
callerid="Meca2" <501>
```

mailbox=501@default voicemail.conf type=friend host=dynamic nat=no context=mecanique [502] secret=1234 callerid="Meca3" <502> mailbox=502@default voicemail.conf type=friend host=dynamic nat=no context=mecanique ; Utilisateurs Production [600] secret=1234 callerid="Prod1" <600> mailbox=600@default voicemail.conf type=friend host=dynamic nat=no context=production [601] secret=1234 callerid="Prod2" <601> mailbox=601@default voicemail.conf

type=friend
host=dynamic
nat=no
context=production

[602]

secret=1234

callerid="Prod3" <602>

mailbox=602@default

voicemail.conf

type=friend

host=dynamic

nat=no

context=production

Configuration Extensions

```
- cp /etc/asterisk/extensions.conf /etc/asterisk/extensions.conf.original
->/etc/asterisk/extensions.conf
- nano /etc/asterisk/extensions.conf
[administration]
exten => _30X,1,Dial(SIP/${EXTEN},10)
exten => _30X,n,VoiceMail(${EXTEN}@default,u)
exten => _30X,n,Hangup()
; Appeler quelqu'un dans la comptabilité (400-402)
exten => _40X,1,Dial(SIP/${EXTEN},10)
exten => _40X,n,Hangup()
; Appeler quelqu'un dans la mécanique (500-502)
exten => _50X,1,Dial(SIP/${EXTEN},10)
exten => _50X,n,Hangup()
; Appeler quelqu'un dans la production (600-602)
exten => _60X,1,Dial(SIP/${EXTEN},10)
exten => _60X,n,Hangup()
; Appeler la comptabilité en cascade puis tout le service
exten => 4000,1,Dial(SIP/400,10)
exten => 4000,n,Dial(SIP/401,10)
exten => 4000,n,Dial(SIP/402,10)
exten => 4000,n,Dial(SIP/400&SIP/401&SIP/402,10)
exten => 4000,n,VoiceMail(400@default,u)
exten => 4000,n,Hangup()
; Écoute messagerie
exten => 888,1,VoiceMailMain(${CALLERID(num)})
```

```
[comptabilite]
exten => _40X,1,Dial(SIP/${EXTEN},10)
exten => _40X,n,VoiceMail(${EXTEN}@default,u)
exten => _40X,n,Hangup()
; Appeler administration
exten => _30X,1,Dial(SIP/${EXTEN},10)
; Appeler mécanique
exten => _50X,1,Dial(SIP/${EXTEN},10)
; Écoute messagerie
exten => 888,1,VoiceMailMain(${CALLERID(num)})
[mecanique]
exten => _50X,1,Dial(SIP/${EXTEN},10)
exten => _50X,n,VoiceMail(${EXTEN}@default,u)
exten => _50X,n,Hangup()
; Appeler production
exten => _60X,1,Dial(SIP/${EXTEN},10)
; Écoute messagerie
exten => 888,1,VoiceMailMain(${CALLERID(num)})
[production]
exten => _60X,1,Dial(SIP/${EXTEN},10)
exten => _60X,n,Hangup()
; Appeler mécanique en cascade
```

exten => 5000,1,Dial(SIP/500,5)

exten => 5000,n,Dial(SIP/501,5)

exten => 5000,n,Dial(SIP/502,5)

exten => 5000,n,VoiceMail(500@default,u)

- → Aller dans la console
- asterisk -rvv
- reload
- sip show users
- systemctl restart asterisk

Configuration Messagerie

- cp /etc/asterisk/voicemail.conf /etc/asterisk/voicemail.conf.original
- ->/etc/asterisk/voicemail.conf
- nano /etc/asterisk/voicemail.conf

[general]

format=ulaw|alaw

attach=yes

serveremail=test@default

emailsubject=Nouveau message de \${VM_CIDNAME}

emailbody= $\n\$ Sonjour ${VM_NAME},\n\$ d'une durée de ${VM_DUR}$ secondes.

maxmsg=20

maxsecs=30

minsecs=2

maxlogins=3

review=yes

saycid=yes

[default]

300 = 1234, Admin1, 300@default

301 = 1234, Admin2, 301@default

302 = 1234, Admin3, 302@default

400 = 1234, Compta1, 400@default

401 = 1234, Compta2, 401@default

402 = 1234, Compta3, 402@default

500 = 1234, Meca1, 500@default

501 = 1234, Meca2, 501@default

502 = 1234, Meca3, 502@default

- → Aller dans la console
- asterisk -rvv
- reload

VM Client Asterisk

- → En NAT
- → Ne rien changer dans les addresses ip, nom de machine etc... tout mettre en automatique.
- → Installer MicroSip > Ajouter un compte > Ecrire les informations suivantes, par exemple :

Nom du compte: 300

Server SIP: 192.168.75.133

Proxy SIP: 192.168.75.133

Nom d'utilisateur : 300

Domaine: m2i.local

Login: 300

Mot de passe: 1234

Transport : UDP + TCP

Sur machine physique

→ Installer MicroSip > Ajouter un compte > Ecrire les informations suivantes, par exemple :

Nom du compte: 400

Server SIP: 192.168.75.133

Proxy SIP: 192.168.75.133

Nom d'utilisateur : 400

Domaine: m2i.local

Login: 400

Mot de passe: 1234

Transport : UDP + TCP