

OpenShift Container Platform 4.8

Scalability and performance

Scaling your OpenShift Container Platform cluster and tuning performance in production environments

Last Updated: 2021-09-09

OpenShift Container Platform 4.8 Scalability and performance

Scaling your OpenShift Container Platform cluster and tuning performance in production environments

Legal Notice

Copyright © 2021 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document provides instructions for scaling your cluster and optimizing the performance of your OpenShift Container Platform environment.

Table of Contents

CHAPTER 1. RECOMMENDED PRACTICES FOR INSTALLING LARGE CLUSTERS 1.1. RECOMMENDED PRACTICES FOR INSTALLING LARGE SCALE CLUSTERS	. 7
CHAPTER 2. RECOMMENDED HOST PRACTICES	. 8
2.1. RECOMMENDED NODE HOST PRACTICES	8
2.2. CREATING A KUBELETCONFIG CRD TO EDIT KUBELET PARAMETERS	9
2.3. MODIFYING THE NUMBER OF UNAVAILABLE WORKER NODES	13
2.4. CONTROL PLANE NODE SIZING	13
2.5. RECOMMENDED ETCD PRACTICES	15
2.6. DEFRAGMENTING ETCD DATA	16
2.7. OPENSHIFT CONTAINER PLATFORM INFRASTRUCTURE COMPONENTS	19
2.8. MOVING THE MONITORING SOLUTION	19
2.9. MOVING THE DEFAULT REGISTRY	20
2.10. MOVING THE ROUTER	22
2.11. INFRASTRUCTURE NODE SIZING	23
2.12. ADDITIONAL RESOURCES	24
CHAPTER 3. RECOMMENDED HOST PRACTICES FOR IBM Z & LINUXONE ENVIRONMENTS	25
3.1. MANAGING CPU OVERCOMMITMENT	25
3.2. HOW TO DISABLE TRANSPARENT HUGE PAGES	25
3.2.1. Disable THP with a Node Tuning Operator (NTO) profile	26
3.3. BOOST NETWORKING PERFORMANCE WITH RECEIVE FLOW STEERING	27
3.3.1. Use the Machine Config Operator (MCO) to activate RFS	27
3.4. CHOOSE YOUR NETWORKING SETUP	28
3.5. ENSURE HIGH DISK PERFORMANCE WITH HYPERPAV ON Z/VM	28
3.5.1. Use the Machine Config Operator (MCO) to activate HyperPAV aliases in nodes using z/VM full-pack minidisks	29
3.6. RHEL KVM ON IBM Z HOST RECOMMENDATIONS	30
3.6.1. Use multiple queues for your VirtlO network interfaces	30
3.6.2. Use I/O threads for your virtual block devices	30
3.6.3. Avoid virtual SCSI devices	31
3.6.4. Configure guest caching for disk	31
3.6.5. Exclude the memory balloon device	31
3.6.6. Tune the CPU migration algorithm of the host scheduler	32
3.6.7. Disable the cpuset cgroup controller	32
3.6.8. Tune the polling period for idle virtual CPUs	33
CHAPTER 4. RECOMMENDED CLUSTER SCALING PRACTICES	34
4.1. RECOMMENDED PRACTICES FOR SCALING THE CLUSTER	34
4.2. MODIFYING A MACHINE SET	34
4.3. ABOUT MACHINE HEALTH CHECKS	35
4.3.1. Limitations when deploying machine health checks	36
4.4. SAMPLE MACHINEHEALTHCHECK RESOURCE	36
4.4.1. Short-circuiting machine health check remediation	37
4.4.1.1. Setting maxUnhealthy by using an absolute value	38
4.4.1.2. Setting maxUnhealthy by using percentages	38
4.5. CREATING A MACHINEHEALTHCHECK RESOURCE	38
CHAPTER 5. USING THE NODE TUNING OPERATOR	40
5.1. ABOUT THE NODE TUNING OPERATOR	40
5.2. ACCESSING AN EXAMPLE NODE TUNING OPERATOR SPECIFICATION	40
5.3. DEFAULT PROFILES SET ON A CLUSTER	41

5.4. VERIFYING THAT THE TUNED PROFILES ARE APPLIED 5.5. CUSTOM TUNING SPECIFICATION 5.6. CUSTOM TUNING EXAMPLES	42 43
5.7. SUPPORTED TUNED DAEMON PLUG-INS	46 48
CHAPTER 6. USING CLUSTER LOADER	50
6.1. INSTALLING CLUSTER LOADER	50
6.2. RUNNING CLUSTER LOADER	50
6.3. CONFIGURING CLUSTER LOADER	51
6.3.1. Example Cluster Loader configuration file	51
6.3.2. Configuration fields	52
6.4. KNOWN ISSUES	55
CHAPTER 7. USING CPU MANAGER	56
7.1. SETTING UP CPU MANAGER	56
CHAPTER 8. USING TOPOLOGY MANAGER	61
8.1. TOPOLOGY MANAGER POLICIES	61
8.2. SETTING UP TOPOLOGY MANAGER	62
8.3. POD INTERACTIONS WITH TOPOLOGY MANAGER POLICIES	62
CHAPTER 9. SCALING THE CLUSTER MONITORING OPERATOR	64
9.1. PROMETHEUS DATABASE STORAGE REQUIREMENTS	64
9.2. CONFIGURING CLUSTER MONITORING	65
CHAPTER 10. THE NODE FEATURE DISCOVERY OPERATOR	67
10.1. ABOUT THE NODE FEATURE DISCOVERY OPERATOR	67
10.2. INSTALLING THE NODE FEATURE DISCOVERY OPERATOR	67
10.2.1. Installing the NFD Operator using the CLI	67
10.2.2. Installing the NFD Operator using the web console	69
10.3. USING THE NODE FEATURE DISCOVERY OPERATOR	69
10.3.1. Create a NodeFeatureDiscovery instance using the CLI	70
10.3.2. Create a NodeFeatureDiscovery CR using the web console	73
10.4. CONFIGURING THE NODE FEATURE DISCOVERY OPERATOR	73
10.4.1. core	73
core.sleepInterval	73
core.sources	73
core.labelWhiteList	74
core.noPublish	74
core.klog	74
core.klog.addDirHeader	74
core.klog.alsologtostderr	74
core.klog.logBacktraceAt	75
core.klog.logDir	75 75
core.klog.logFile	75 75
core.klog.logFileMaxSize	75 75
core.klog.logtostderr	75 75
core.klog.skipHeaders	75 75
core.klog.skipLogHeaders	75 75
core.klog.stderrthreshold	
core.klog.v	76 76
core.klog.vmodule 10.4.2. sources	76 76
	76 76
sources.cpu.cpuid.attributeBlacklist	76

sources.cpu.cpuid.attributeWhitelist	76
sources.kernel.kconfigFile	76
sources.kernel.configOpts	77
soures.pci.deviceClassWhitelist	77
soures.pci.deviceLabelFields	77
soures.usb.deviceClassWhitelist	77
soures.usb.deviceLabelFields	78
soures.custom	78
CHAPTER 11. THE DRIVER TOOLKIT	79
11.1. ABOUT THE DRIVER TOOLKIT	79
Background	79
Purpose	80
11.2. PULLING THE DRIVER TOOLKIT CONTAINER IMAGE	80
11.2.1. Pulling the Driver Toolkit container image from registry.redhat.io	80
11.2.2. Finding the Driver Toolkit image URL in the payload	80
11.3. USING THE DRIVER TOOLKIT	81
11.3.1. Build and run the simple-kmod driver container on a cluster	81
CHAPTER 12. PLANNING YOUR ENVIRONMENT ACCORDING TO OBJECT MAXIMUMS	86
12.1. OPENSHIFT CONTAINER PLATFORM TESTED CLUSTER MAXIMUMS FOR MAJOR RELEASES	86
12.2. OPENSHIFT CONTAINER PLATFORM TESTED CLUSTER MAXIMUMS	87
12.3. OPENSHIFT CONTAINER PLATFORM ENVIRONMENT AND CONFIGURATION ON WHICH THE CLUS	
MAXIMUMS ARE TESTED	89
12.4. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO TESTED CLUSTER MAXIMUMS	90
12.5. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO APPLICATION REQUIREMENTS	91
CHAPTER 13. OPTIMIZING STORAGE	95
13.1. AVAILABLE PERSISTENT STORAGE OPTIONS	95
13.2. RECOMMENDED CONFIGURABLE STORAGE TECHNOLOGY	96
13.2.1. Specific application storage recommendations	96
13.2.1.1. Registry	97
13.2.1.2. Scaled registry	97
13.2.1.3. Metrics	97
13.2.1.4. Logging	98
13.2.1.5. Applications	98
13.2.2. Other specific application storage recommendations	98
13.3. DATA STORAGE MANAGEMENT	98
CHAPTER 14. OPTIMIZING ROUTING	100
14.1. BASELINE INGRESS CONTROLLER (ROUTER) PERFORMANCE	100
14.2. INGRESS CONTROLLER (ROUTER) PERFORMANCE OPTIMIZATIONS	101
CHAPTER 15. OPTIMIZING NETWORKING	102
15.1. OPTIMIZING THE MTU FOR YOUR NETWORK	102
15.2. RECOMMENDED PRACTICES FOR INSTALLING LARGE SCALE CLUSTERS	103
15.3. IMPACT OF IPSEC	103
CHAPTER 16. MANAGING BARE METAL HOSTS	104
16.1. ABOUT BARE METAL HOSTS AND NODES	104
16.2. MAINTAINING BARE METAL HOSTS	104
16.2.1. Adding a bare metal host to the cluster using the web console	104
16.2.2. Adding a bare metal host to the cluster using YAML in the web console	105
16.2.3. Automatically scaling machines to the number of available bare metal hosts	106

CHAPTER 17. WHAT HUGE PAGES DO AND HOW THEY ARE CONSUMED BY APPLICATIONS	108
17.1. WHAT HUGE PAGES DO	108
17.2. HOW HUGE PAGES ARE CONSUMED BY APPS	108
17.3. CONSUMING HUGE PAGES RESOURCES USING THE DOWNWARD API	109
17.4. CONFIGURING HUGE PAGES	111
17.4.1. At boot time	111
CHAPTER 18. PERFORMANCE ADDON OPERATOR FOR LOW LATENCY NODES	114
18.1. UNDERSTANDING LOW LATENCY 18.1.1. About hyperthreading for low latency and real-time applications	114 114
18.2. INSTALLING THE PERFORMANCE ADDON OPERATOR	115
18.2.1. Installing the Operator using the CLI	115
18.2.2. Installing the Performance Addon Operator using the web console	116
18.3. UPGRADING PERFORMANCE ADDON OPERATOR	117
18.3.1. About upgrading Performance Addon Operator	117
18.3.1.1. How Performance Addon Operator upgrades affect your cluster	118
18.3.1.2. Upgrading Performance Addon Operator to the next minor version	118
18.3.1.3. Upgrading Performance Addon Operator when previously installed to a specific namespace	118
18.3.2. Monitoring upgrade status	119
18.4. PROVISIONING REAL-TIME AND LOW LATENCY WORKLOADS	120
18.4.1. Known limitations for real-time	120
18.4.2. Provisioning a worker with real-time capabilities	120
18.4.3. Verifying the real-time kernel installation	121
18.4.4. Creating a workload that works in real-time	121
18.4.5. Creating a pod with a QoS class of Guaranteed	122
18.4.6. Optional: Disabling CPU load balancing for DPDK	123
18.4.7. Assigning a proper node selector	123
18.4.8. Scheduling a workload onto a worker with real-time capabilities	124
18.4.9. Managing device interrupt processing for guaranteed pod isolated CPUs	124
18.4.9.1. Disabling global device interrupts handling in Performance Addon Operator	124
18.4.9.2. Disabling interrupt processing for individual pods	125
18.4.10. Upgrading the performance profile to use device interrupt processing	125
18.4.10.1. Supported API Versions	125
18.4.10.1.1. Upgrading Performance Addon Operator API from v1alpha1 to v1 18.4.10.1.2. Upgrading Performance Addon Operator API from v1alpha1 or v1 to v2	125 125
18.4.11. Configuring a node for IRQ dynamic load balancing	125
18.4.12. Configuring hyperthreading for a cluster	128
18.4.12.1. Disabling hyperthreading for low latency applications	130
18.5. TUNING NODES FOR LOW LATENCY WITH THE PERFORMANCE PROFILE	131
18.5.1. Configuring huge pages	132
18.5.2. Allocating multiple huge page sizes	133
18.5.3. Restricting CPUs for infra and application containers	133
18.6. REDUCING NIC QUEUES USING THE PERFORMANCE ADDON OPERATOR	134
18.6.1. Adjusting the NIC queues with the performance profile	134
18.6.2. Verifying the queue status	137
18.6.3. Logging associated with adjusting NIC queues	141
18.7. PERFORMING END-TO-END TESTS FOR PLATFORM VERIFICATION	141
18.7.1. Prerequisites	142
18.7.2. Running the tests	143
18.7.2.1. Running the latency tests	143
18.7.3. Image parameters	145
18.7.3.1. Ginkgo parameters	145
18.7.3.2. Available features	145

	18.7.4. Dry run	146
	18.7.5. Disconnected mode	146
	18.7.5.1. Mirroring the images to a custom registry accessible from the cluster	146
	18.7.5.2. Instruct the tests to consume those images from a custom registry	146
	18.7.5.3. Mirroring to the cluster internal registry	146
	18.7.5.4. Mirroring a different set of images	148
	18.7.6. Discovery mode	148
	18.7.6.1. Required environment configuration prerequisites	149
	18.7.6.2. Limiting the nodes used during tests	150
	18.7.6.3. Using a single performance profile	150
	18.7.6.4. Disabling the performance profile cleanup	151
	18.7.7. Running in a single node cluster	151
	Required parameters	152
	18.7.8. Troubleshooting	152
	18.7.9. Test reports	152
	18.7.9.1. JUnit test output	152
	18.7.9.2. Test failure report	152
	18.7.9.3. A note on podman	152
	18.7.9.4. Running on OpenShift Container Platform 4.4	152
	18.7.9.5. Using a single performance profile	153
	18.7.10. Impacts on the cluster	153
	18.7.10.1. SCTP	154
	18.7.10.2. XT_U32	154
	18.7.10.3. SR-IOV	154
	18.7.10.4. PTP	154
	18.7.10.5. Performance	154
	18.7.10.6. DPDK	154
	18.7.10.7. Container-mount-namespace	154
	18.7.10.8. Cleaning up	154
	18.8. DEBUGGING LOW LATENCY CNF TUNING STATUS	154
	18.8.1. Machine config pools	156
	18.9. COLLECTING LOW LATENCY TUNING DEBUGGING DATA FOR RED HAT SUPPORT	157
	18.9.1. About the must-gather tool	157
	18.9.2. About collecting low latency tuning data	157
	18.9.3. Gathering data about specific features	158
CI	IAPTER 19. CREATING A PERFORMANCE PROFILE	160
	19.1. ABOUT THE PERFORMANCE PROFILE CREATOR	160
	19.1.1. Gathering data about your cluster using must-gather	160
	19.1.2. Running the Performance Profile Creator using podman	161
	19.1.2.1. How to run podman to create a performance profile	163
	19.1.3. Running the Performance Profile Creator wrapper script	164
	19.1.4. Performance Profile Creator arguments	169
	19.2. ADDITIONAL RESOURCES	171

CHAPTER 1. RECOMMENDED PRACTICES FOR INSTALLING LARGE CLUSTERS

Apply the following practices when installing large clusters or scaling clusters to larger node counts.

1.1. RECOMMENDED PRACTICES FOR INSTALLING LARGE SCALE CLUSTERS

When installing large clusters or scaling the cluster to larger node counts, set the cluster network **cidr** accordingly in your **install-config.yaml** file before you install the cluster:

networking:

clusterNetwork:
- cidr: 10.128.0.0/14
hostPrefix: 23

machineCIDR: 10.0.0.0/16 networkType: OpenShiftSDN

serviceNetwork: - 172.30.0.0/16

The default cluster network **cidr 10.128.0.0/14** cannot be used if the cluster size is more than 500 nodes. It must be set to **10.128.0.0/12** or **10.128.0.0/10** to get to larger node counts beyond 500 nodes.

CHAPTER 2. RECOMMENDED HOST PRACTICES

This topic provides recommended host practices for OpenShift Container Platform.



IMPORTANT

These guidelines apply to OpenShift Container Platform with software-defined networking (SDN), not Open Virtual Network (OVN).

2.1. RECOMMENDED NODE HOST PRACTICES

The OpenShift Container Platform node configuration file contains important options. For example, two parameters control the maximum number of pods that can be scheduled to a node: **podsPerCore** and **maxPods**.

When both options are in use, the lower of the two values limits the number of pods on a node. Exceeding these values can result in:

- Increased CPU utilization.
- Slow pod scheduling.
- Potential out-of-memory scenarios, depending on the amount of memory in the node.
- Exhausting the pool of IP addresses.
- Resource overcommitting, leading to poor user application performance.



IMPORTANT

In Kubernetes, a pod that is holding a single container actually uses two containers. The second container is used to set up networking prior to the actual container starting. Therefore, a system running 10 pods will actually have 20 containers running.



NOTE

Disk IOPS throttling from the cloud provider might have an impact on CRI-O and kubelet. They might get overloaded when there are large number of I/O intensive pods running on the nodes. It is recommended that you monitor the disk I/O on the nodes and use volumes with sufficient throughput for the workload.

podsPerCore sets the number of pods the node can run based on the number of processor cores on the node. For example, if **podsPerCore** is set to **10** on a node with 4 processor cores, the maximum number of pods allowed on the node will be **40**.

kubeletConfig:
 podsPerCore: 10

Setting **podsPerCore** to **0** disables this limit. The default is **0**. **podsPerCore** cannot exceed **maxPods**.

maxPods sets the number of pods the node can run to a fixed value, regardless of the properties of the node.

kubeletConfig: maxPods: 250

2.2. CREATING A KUBELETCONFIG CRD TO EDIT KUBELET PARAMETERS

The kubelet configuration is currently serialized as an Ignition configuration, so it can be directly edited. However, there is also a new **kubelet-config-controller** added to the Machine Config Controller (MCC). This allows you to use a **KubeletConfig** custom resource (CR) to edit the kubelet parameters.

You should have one **KubeletConfig** CR for each machine config pool with all the config changes you want for that pool. If you are applying the same content to all the pools, you only need one **KubeletConfig** CR for all the pools.

You should edit an existing **KubeletConfig** CR to modify existing settings or add new settings instead of creating a new CR for each change. It is recommended to create a new CR only to modify a different machine config pool, or for changes that are intended to be temporary so that you can revert the changes.

You can create multiple **KubeletConfig** CRs, as needed, with a limit of 10 per cluster. For the first **KubeletConfig** CR, the MCO creates a machine config appended with **kubelet**. With each subsequent CR, the controller creates a new **kubelet** machine config with a numeric suffix. For example, if you have a **kubelet** machine config with a **-2** suffix, the next **kubelet** machine config is appended with **-3**.

If you want to delete the machine configs, you should delete them in reverse order to avoid exceeding the limit. For example, you should delete the **kubelet-3** machine config before deleting the **kubelet-2** machine config.



NOTE

If you have a machine config with a **kubelet-9** suffix, and you create another **KubeletConfig** CR, a new machine config is not created, even if there are fewer than 10 **kubelet** machine configs.

Example KubeletConfig CR

\$ oc get kubeletconfig

NAME AGE set-max-pods 15m

Example showing a KubeletConfig machine config

\$ oc get mc | grep kubelet

99-worker-generated-kubelet-1 26m

b5c5119de007945b6fe6fb215db3b8e2ceb12511 3.2.0

9

The following procedure is an example to show how to configure the maximum number of pods per node on the worker nodes.

Prerequisites

- 1. Obtain the label associated with the static **MachineConfigPool** CR for the type of node you want to configure. Perform one of the following steps:
 - a. View the machine config pool:

\$ oc describe machineconfigpool <name>

For example:

\$ oc describe machineconfigpool worker

Example output

apiVersion: machineconfiguration.openshift.io/v1

kind: MachineConfigPool

metadata:

creationTimestamp: 2019-02-08T14:52:39Z

generation: 1

labels:

custom-kubelet: set-max-pods 1

- 1 If a label has been added it appears under labels.
- b. If the label is not present, add a key/value pair:

\$ oc label machineconfigpool worker custom-kubelet=set-max-pods

Procedure

- 1. View the available machine configuration objects that you can select:
 - \$ oc get machineconfig

By default, the two kubelet-related configs are **01-master-kubelet** and **01-worker-kubelet**.

2. Check the current value for the maximum pods per node:

\$ oc describe node <node_name>

For example:

\$ oc describe node ci-ln-5grqprb-f76d1-ncnqq-worker-a-mdv94

Look for value: pods: <value> in the Allocatable stanza:

Example output

Allocatable:

attachable-volumes-aws-ebs: 25 cpu: 3500m

hugepages-1Gi: 0 hugepages-2Mi: 0

memory: 15341844Ki

pods: 250

3. Set the maximum pods per node on the worker nodes by creating a custom resource file that contains the kubelet configuration:

apiVersion: machineconfiguration.openshift.io/v1

kind: KubeletConfig

metadata:

name: set-max-pods

spec

machineConfigPoolSelector:

matchLabels:

custom-kubelet: set-max-pods 1

kubeletConfig: maxPods: 500 2

- Enter the label from the machine config pool.
- 2 Add the kubelet configuration. In this example, use **maxPods** to set the maximum pods per node.



NOTE

The rate at which the kubelet talks to the API server depends on queries per second (QPS) and burst values. The default values, **50** for **kubeAPIQPS** and **100** for **kubeAPIBurst**, are sufficient if there are limited pods running on each node. It is recommended to update the kubelet QPS and burst rates if there are enough CPU and memory resources on the node.

apiVersion: machineconfiguration.openshift.io/v1

kind: KubeletConfig

metadata:

name: set-max-pods

spec:

machineConfigPoolSelector:

matchLabels:

custom-kubelet: set-max-pods

kubeletConfig:

maxPods: <pod_count> kubeAPIBurst: <burst_rate> kubeAPIQPS: <QPS>

a. Create the KubeletConfig object:

\$ oc create -f change-maxPods-cr.yaml

b. Verify that the **KubeletConfig** object is created:

\$ oc get kubeletconfig

Example output

NAME AGE set-max-pods 15m

Depending on the number of worker nodes in the cluster, wait for the worker nodes to be rebooted one by one. For a cluster with 3 worker nodes, this could take about 10 to 15 minutes.

- 4. Verify that the changes are applied to the node:
 - a. Check on a worker node that the **maxPods** value changed:

\$ oc describe node <node_name>

b. Locate the **Allocatable** stanza:

Allocatable:
attachable-volumes-gce-pd: 127
cpu: 3500m
ephemeral-storage: 123201474766
hugepages-1Gi: 0
hugepages-2Mi: 0
memory: 14225400Ki
pods: 500 1

- In this example, the **pods** parameter should report the value you set in the **KubeletConfig** object.
- 5. Verify the change in the **KubeletConfig** object:

\$ oc get kubeletconfigs set-max-pods -o yaml

This should show a **status: "True"** and **type:Success**:

```
spec:
kubeletConfig:
maxPods: 500
machineConfigPoolSelector:
matchLabels:
custom-kubelet: set-max-pods
status:
conditions:
- lastTransitionTime: "2021-06-30T17:04:07Z"
message: Success
status: "True"
type: Success
```

2.3. MODIFYING THE NUMBER OF UNAVAILABLE WORKER NODES

By default, only one machine is allowed to be unavailable when applying the kubelet-related configuration to the available worker nodes. For a large cluster, it can take a long time for the configuration change to be reflected. At any time, you can adjust the number of machines that are updating to speed up the process.

Procedure

1. To edit the **worker** machine config pool, run the following command:

\$ oc edit machineconfigpool worker

2. Add the **maxUnavailable** parameter and value to the spec:

spec:

maxUnavailable: <node_count>



IMPORTANT

When setting the value, consider the number of worker nodes that can be unavailable without affecting the applications running on the cluster.

2.4. CONTROL PLANE NODE SIZING

The control plane node resource requirements depend on the number of nodes in the cluster. The following control plane node size recommendations are based on the results of control plane density focused testing. The control plane tests create the following objects across the cluster in each of the namespaces depending on the node counts:

- 12 image streams
- 3 build configurations
- 6 builds
- 1 deployment with 2 pod replicas mounting two secrets each
- 2 deployments with 1 pod replica mounting two secrets
- 3 services pointing to the previous deployments
- 3 routes pointing to the previous deployments
- 10 secrets, 2 of which are mounted by the previous deployments
- 10 config maps, 2 of which are mounted by the previous deployments

Number of worker nodes	Cluster load (namespaces)	CPU cores	Memory (GB)
25	500	4	16

Number of worker nodes	Cluster load (namespaces)	CPU cores	Memory (GB)
100	1000	8	32
250	4000	16	96

On a large and dense cluster with three masters or control plane nodes, the CPU and memory usage will spike up when one of the nodes is stopped, rebooted or fails. The failures can be due to unexpected issues with power, network or underlying infrastructure in addition to intentional cases where the cluster is restarted after shutting it down to save costs. The remaining two control plane (also known as master) nodes must handle the load in order to be highly available which leads to increase in the resource usage. This is also expected during upgrades because the masters are cordoned, drained, and rebooted serially to apply the operating system updates, as well as the control plane Operators update. To avoid cascading failures, keep the overall resource usage on the control plane nodes (also known as the master nodes) to at most half of all available capacity to handle the resource usage spikes. Increase the CPU and memory on the control plane nodes accordingly to avoid potential downtime due to lack of resources.



IMPORTANT

The node sizing varies depending on the number of nodes and object counts in the cluster. It also depends on whether the objects are actively being created on the cluster. During object creation, the control plane is more active in terms of resource usage compared to when the objects are in the **running** phase.

Operator Lifecycle Manager (OLM) runs on the control plane nodes and it's memory footprint depends on the number of namespaces and user installed operators that OLM needs to manage on the cluster. Control plane nodes need to be sized accordingly to avoid OOM kills. Following data points are based on the results from cluster maximums testing.

Number of namespaces	OLM memory at idle state (GB)	OLM memory with 5 user operators installed (GB)
500	0.823	1.7
1000	1.2	2.5
1500	1.7	3.2
2000	2	4.4
3000	2.7	5.6
4000	3.8	7.6
5000	4.2	9.02

Number of namespaces	OLM memory at idle state (GB)	OLM memory with 5 user operators installed (GB)
6000	5.8	11.3
7000	6.6	12.9
8000	6.9	14.8
9000	8	17.7
10,000	9.9	21.6



IMPORTANT

If you used an installer-provisioned infrastructure installation method, you cannot modify the control plane node size in a running OpenShift Container Platform 4.8 cluster. Instead, you must estimate your total node count and use the suggested control plane node size during installation.



IMPORTANT

The recommendations are based on the data points captured on OpenShift Container Platform clusters with OpenShift SDN as the network plug-in.



NOTE

In OpenShift Container Platform 4.8, half of a CPU core (500 millicore) is now reserved by the system by default compared to OpenShift Container Platform 3.11 and previous versions. The sizes are determined taking that into consideration.

2.5. RECOMMENDED ETCD PRACTICES

For large and dense clusters, etcd can suffer from poor performance if the keyspace grows excessively large and exceeds the space quota. Periodic maintenance of etcd, including defragmentation, must be performed to free up space in the data store. It is highly recommended that you monitor Prometheus for etcd metrics and defragment it when required before etcd raises a cluster-wide alarm that puts the cluster into a maintenance mode, which only accepts key reads and deletes. Some of the key metrics to monitor are etcd_server_quota_backend_bytes which is the current quota limit, etcd_mvcc_db_total_size_in_use_in_bytes which indicates the actual database usage after a history compaction, and etcd_debugging_mvcc_db_total_size_in_bytes which shows the database size including free space waiting for defragmentation. Instructions on defragging etcd can be found in the Defragmenting etcd data section.

Etcd writes data to disk, so its performance strongly depends on disk performance. Etcd persists proposals on disk. Slow disks and disk activity from other processes might cause long fsync latencies, causing etcd to miss heartbeats, inability to commit new proposals to the disk on time, which can cause request timeouts and temporary leader loss. It is highly recommended to run etcd on machines backed by SSD/NVMe disks with low latency and high throughput.

Some of the key metrics to monitor on a deployed OpenShift Container Platform cluster are p99 of

etcd disk write ahead log duration and the number of etcd leader changes. Use Prometheus to track these metrics. **etcd_disk_wal_fsync_duration_seconds_bucket** reports the etcd disk fsync duration, **etcd_server_leader_changes_seen_total** reports the leader changes. To rule out a slow disk and confirm that the disk is reasonably fast, 99th percentile of the **etcd_disk_wal_fsync_duration_seconds_bucket** should be less than 10ms.

Fio, a I/O benchmarking tool can be used to validate the hardware for etcd before or after creating the OpenShift Container Platform cluster. Run fio and analyze the results:

Assuming container runtimes like podman or docker are installed on the machine under test and the path etcd writes the data exists - /var/lib/etcd, run:

Procedure

Run the following if using podman:

\$ sudo podman run --volume /var/lib/etcd:/var/lib/etcd:Z quay.io/openshift-scale/etcd-perf

Alternatively, run the following if using docker:

\$ sudo docker run --volume /var/lib/etcd:/var/lib/etcd:Z quay.io/openshift-scale/etcd-perf

The output reports whether the disk is fast enough to host etcd by comparing the 99th percentile of the fsync metric captured from the run to see if it is less than 10ms.

Etcd replicates the requests among all the members, so its performance strongly depends on network input/output (IO) latency. High network latencies result in etcd heartbeats taking longer than the election timeout, which leads to leader elections that are disruptive to the cluster. A key metric to monitor on a deployed OpenShift Container Platform cluster is the 99th percentile of etcd network peer latency on each etcd cluster member. Use Prometheus to track the metric. histogram_quantile(0.99, rate(etcd_network_peer_round_trip_time_seconds_bucket[2m])) reports the round trip time for etcd to finish replicating the client requests between the members; it should be less than 50 ms.

2.6. DEFRAGMENTING ETCD DATA

Manual defragmentation must be performed periodically to reclaim disk space after etcd history compaction and other events cause disk fragmentation.

History compaction is performed automatically every five minutes and leaves gaps in the back-end database. This fragmented space is available for use by etcd, but is not available to the host file system. You must defragment etcd to make this space available to the host file system.

Because etcd writes data to disk, its performance strongly depends on disk performance. Consider defragmenting etcd every month, twice a month, or as needed for your cluster. You can also monitor the **etcd_db_total_size_in_bytes** metric to determine whether defragmentation is necessary.



WARNING

Defragmenting etcd is a blocking action. The etcd member will not response until defragmentation is complete. For this reason, wait at least one minute between defragmentation actions on each of the pods to allow the cluster to recover.

Follow this procedure to defragment etcd data on each etcd member.

Prerequisites

• You have access to the cluster as a user with the **cluster-admin** role.

Procedure

- 1. Determine which etcd member is the leader, because the leader should be defragmented last.
 - a. Get the list of etcd pods:

\$ oc get pods -n openshift-etcd -o wide | grep -v quorum-guard | grep etcd

Example output

```
      etcd-ip-10-0-159-225.example.redhat.com
      3/3
      Running
      0
      175m

      10.0.159.225
      ip-10-0-159-225.example.redhat.com
      <none>
      <none>

      etcd-ip-10-0-191-37.example.redhat.com
      3/3
      Running
      0
      173m

      10.0.191.37
      ip-10-0-191-37.example.redhat.com
      <none>
      <none>

      etcd-ip-10-0-199-170.example.redhat.com
      3/3
      Running
      0
      176m

      10.0.199.170
      ip-10-0-199-170.example.redhat.com
      <none>
      <none>
```

b. Choose a pod and run the following command to determine which etcd member is the leader:

 $\$ oc rsh -n openshift-etcd etcd-ip-10-0-159-225.us-west-1.compute.internal etcdctl endpoint status --cluster -w table

Example output

Based on the **IS LEADER** column of this output, the **https://10.0.199.170:2379** endpoint is the leader. Matching this endpoint with the output of the previous step, the pod name of the leader is **etcd-ip-10-0-199-170.example.redhat.com**.

2. Defragment an etcd member.

- a. Connect to the running etcd container, passing in the name of a pod that is *not* the leader:
 - \$ oc rsh -n openshift-etcd etcd-ip-10-0-159-225.example.redhat.com
- b. Unset the **ETCDCTL ENDPOINTS** environment variable:
 - sh-4.4# unset ETCDCTL_ENDPOINTS
- c. Defragment the etcd member:
 - sh-4.4# etcdctl --command-timeout=30s --endpoints=https://localhost:2379 defrag

Example output

Finished defragmenting etcd member[https://localhost:2379]

If a timeout error occurs, increase the value for **--command-timeout** until the command succeeds.

- d. Verify that the database size was reduced:
 - sh-4.4# etcdctl endpoint status -w table --cluster

Example output

This example shows that the database size for this etcd member is now 41 MB as opposed to the starting size of 104 MB.

- e. Repeat these steps to connect to each of the other etcd members and defragment them. Always defragment the leader last.
 - Wait at least one minute between defragmentation actions to allow the etcd pod to recover. Until the etcd pod recovers, the etcd member will not respond.
- 3. If any **NOSPACE** alarms were triggered due to the space quota being exceeded, clear them.
 - a. Check if there are any **NOSPACE** alarms:
 - sh-4.4# etcdctl alarm list

Example output

memberID:12345678912345678912 alarm:NOSPACE

b. Clear the alarms:

sh-4.4# etcdctl alarm disarm

2.7. OPENSHIFT CONTAINER PLATFORM INFRASTRUCTURE COMPONENTS

The following infrastructure workloads do not incur OpenShift Container Platform worker subscriptions:

- Kubernetes and OpenShift Container Platform control plane services that run on masters
- The default router
- The integrated container image registry
- The cluster metrics collection, or monitoring service, including components for monitoring userdefined projects
- Cluster aggregated logging
- Service brokers
- Red Hat Quay
- Red Hat OpenShift Container Storage
- Red Hat Advanced Cluster Manager

Any node that runs any other container, pod, or component is a worker node that your subscription must cover.

2.8. MOVING THE MONITORING SOLUTION

By default, the Prometheus Cluster Monitoring stack, which contains Prometheus, Grafana, and AlertManager, is deployed to provide cluster monitoring. It is managed by the Cluster Monitoring Operator. To move its components to different machines, you create and apply a custom config map.

Procedure

1. Save the following **ConfigMap** definition as the **cluster-monitoring-configmap.yaml** file:

apiVersion: v1
kind: ConfigMap
metadata:
name: cluster-monitoring-config
namespace: openshift-monitoring
data:
config.yaml: |+
alertmanagerMain:
nodeSelector:

```
node-role.kubernetes.io/infra: ""
prometheusK8s:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
prometheusOperator:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
grafana:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
k8sPrometheusAdapter:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
kubeStateMetrics:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
telemeterClient:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
openshiftStateMetrics:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
thanosQuerier:
 nodeSelector:
  node-role.kubernetes.io/infra: ""
```

Running this config map forces the components of the monitoring stack to redeploy to infrastructure nodes.

- 2. Apply the new config map:
 - \$ oc create -f cluster-monitoring-configmap.yaml
- 3. Watch the monitoring pods move to the new machines:
 - \$ watch 'oc get pod -n openshift-monitoring -o wide'
- 4. If a component has not moved to the **infra** node, delete the pod with this component:
 - \$ oc delete pod -n openshift-monitoring <pod>

The component from the deleted pod is re-created on the **infra** node.

2.9. MOVING THE DEFAULT REGISTRY

You configure the registry Operator to deploy its pods to different nodes.

Prerequisites

• Configure additional machine sets in your OpenShift Container Platform cluster.

Procedure

1. View the **config/instance** object:

\$ oc get configs.imageregistry.operator.openshift.io/cluster -o yaml

Example output

```
apiVersion: imageregistry.operator.openshift.io/v1
kind: Config
metadata:
 creationTimestamp: 2019-02-05T13:52:05Z
 - imageregistry.operator.openshift.io/finalizer
 generation: 1
 name: cluster
 resourceVersion: "56174"
 selfLink: /apis/imageregistry.operator.openshift.io/v1/configs/cluster
 uid: 36fd3724-294d-11e9-a524-12ffeee2931b
spec:
 httpSecret: d9a012ccd117b1e6616ceccb2c3bb66a5fed1b5e481623
 logging: 2
 managementState: Managed
 proxy: {}
 replicas: 1
 requests:
  read: {}
  write: {}
 storage:
  s3:
   bucket: image-registry-us-east-1-c92e88cad85b48ec8b312344dff03c82-392c
   region: us-east-1
status:
```

2. Edit the **config/instance** object:

\$ oc edit configs.imageregistry.operator.openshift.io/cluster

3. Modify the **spec** section of the object to resemble the following YAML:

```
spec:
affinity:
podAntiAffinity:
preferredDuringSchedulingIgnoredDuringExecution:
- podAffinityTerm:
namespaces:
- openshift-image-registry
topologyKey: kubernetes.io/hostname
weight: 100
logLevel: Normal
managementState: Managed
nodeSelector:
node-role.kubernetes.io/infra: ""
```

- 4. Verify the registry pod has been moved to the infrastructure node.
 - a. Run the following command to identify the node where the registry pod is located:

\$ oc get pods -o wide -n openshift-image-registry

b. Confirm the node has the label you specified:

\$ oc describe node <node_name>

Review the command output and confirm that **node-role.kubernetes.io/infra** is in the **LABELS** list.

2.10. MOVING THE ROUTER

You can deploy the router pod to a different machine set. By default, the pod is deployed to a worker node.

Prerequisites

• Configure additional machine sets in your OpenShift Container Platform cluster.

Procedure

1. View the **IngressController** custom resource for the router Operator:

\$ oc get ingresscontroller default -n openshift-ingress-operator -o yaml

The command output resembles the following text:

```
apiVersion: operator.openshift.io/v1
kind: IngressController
metadata:
 creationTimestamp: 2019-04-18T12:35:39Z
 finalizers:
 - ingresscontroller.operator.openshift.io/finalizer-ingresscontroller
 generation: 1
 name: default
 namespace: openshift-ingress-operator
 resourceVersion: "11341"
 selfLink: /apis/operator.openshift.io/v1/namespaces/openshift-ingress-
operator/ingresscontrollers/default
 uid: 79509e05-61d6-11e9-bc55-02ce4781844a
spec: {}
status:
 availableReplicas: 2
 conditions:
 - lastTransitionTime: 2019-04-18T12:36:15Z
  status: "True"
  type: Available
 domain: apps.<cluster>.example.com
 endpointPublishingStrategy:
  type: LoadBalancerService
 selector: ingresscontroller.operator.openshift.io/deployment-ingresscontroller=default
```

2. Edit the **ingresscontroller** resource and change the **nodeSelector** to use the **infra** label:

\$ oc edit ingresscontroller default -n openshift-ingress-operator

Add the **nodeSelector** stanza that references the **infra** label to the **spec** section, as shown:

```
spec:
nodePlacement:
nodeSelector:
matchLabels:
node-role.kubernetes.io/infra: ""
```

- 3. Confirm that the router pod is running on the **infra** node.
 - a. View the list of router pods and note the node name of the running pod:

\$ oc get pod -n openshift-ingress -o wide

Example output

```
STATUS
NAME
                     READY
                                          RESTARTS AGE
                                                             IΡ
                                                                     NODE
NOMINATED NODE READINESS GATES
router-default-86798b4b5d-bdlvd 1/1
                                             0
                                                    28s
                                                          10.130.2.4 ip-10-
                                   Running
0-217-226.ec2.internal <none>
                                <none>
router-default-955d875f4-255g8 0/1
                                  Terminating 0
                                                    19h
                                                           10.129.2.4 ip-10-
0-148-172.ec2.internal <none>
                                <none>
```

In this example, the running pod is on the ip-10-0-217-226.ec2.internal node.

b. View the node status of the running pod:

```
$ oc get node <node_name> 1
```

Specify the <node_name> that you obtained from the pod list.

Example output

```
NAME STATUS ROLES AGE VERSION ip-10-0-217-226.ec2.internal Ready infra,worker 17h v1.21.0
```

Because the role list includes **infra**, the pod is running on the correct node.

2.11. INFRASTRUCTURE NODE SIZING

Infrastructure nodes are nodes that are labeled to run pieces of the OpenShift Container Platform environment. The infrastructure node resource requirements depend on the cluster age, nodes, and objects in the cluster, as these factors can lead to an increase in the number of metrics or time series in Prometheus. The following infrastructure node size recommendations are based on the results of cluster maximums and control plane density focused testing.

Number of worker nodes	CPU cores	Memory (GB)
25	4	16
100	8	32
250	16	128
500	32	128

In general, three infrastructure nodes are recommended per cluster.



IMPORTANT

These sizing recommendations are based on scale tests, which create a large number of objects across the cluster. These tests include reaching some of the cluster maximums. In the case of 250 and 500 node counts on a OpenShift Container Platform 4.8 cluster, these maximums are 10000 namespaces with 61000 pods, 10000 deployments, 181000 secrets, 400 config maps, and so on. Prometheus is a highly memory intensive application; the resource usage depends on various factors including the number of nodes, objects, the Prometheus metrics scraping interval, metrics or time series, and the age of the cluster. The disk size also depends on the retention period. You must take these factors into consideration and size them accordingly.

These sizing recommendations are only applicable for the Prometheus, Router, and Registry infrastructure components, which are installed during cluster installation. Logging is a day-two operation and is not included in these recommendations.



NOTE

In OpenShift Container Platform 4.8, half of a CPU core (500 millicore) is now reserved by the system by default compared to OpenShift Container Platform 3.11 and previous versions. This influences the stated sizing recommendations.

2.12. ADDITIONAL RESOURCES

- OpenShift Container Platform cluster maximums
- Creating infrastructure machine sets

CHAPTER 3. RECOMMENDED HOST PRACTICES FOR IBM Z & LINUXONE ENVIRONMENTS

This topic provides recommended host practices for OpenShift Container Platform on IBM Z and LinuxONE.



NOTE

The s390x architecture is unique in many aspects. Therefore, some recommendations made here might not apply to other platforms.



NOTE

Unless stated otherwise, these practices apply to both z/VM and Red Hat Enterprise Linux (RHEL) KVM installations on IBM Z and LinuxONE.

3.1. MANAGING CPU OVERCOMMITMENT

In a highly virtualized IBM Z environment, you must carefully plan the infrastructure setup and sizing. One of the most important features of virtualization is the capability to do resource overcommitment, allocating more resources to the virtual machines than actually available at the hypervisor level. This is very workload dependent and there is no golden rule that can be applied to all setups.

Depending on your setup, consider these best practices regarding CPU overcommitment:

- At LPAR level (PR/SM hypervisor), avoid assigning all available physical cores (IFLs) to each LPAR. For example, with four physical IFLs available, you should not define three LPARs with four logical IFLs each.
- Check and understand LPAR shares and weights.
- An excessive number of virtual CPUs can adversely affect performance. Do not define more virtual processors to a guest than logical processors are defined to the LPAR.
- Configure the number of virtual processors per guest for peak workload, not more.
- Start small and monitor the workload. Increase the vCPU number incrementally if necessary.
- Not all workloads are suitable for high overcommitment ratios. If the workload is CPU intensive, you will probably not be able to achieve high ratios without performance problems. Workloads that are more I/O intensive can keep consistent performance even with high overcommitment ratios.

Additional resources

- z/VM Common Performance Problems and Solutions
- z/VM overcommitment considerations
- LPAR CPU management

3.2. HOW TO DISABLE TRANSPARENT HUGE PAGES

Transparent Huge Pages (THP) attempt to automate most aspects of creating, managing, and using

huge pages. Since THP automatically manages the huge pages, this is not always handled optimally for all types of workloads. THP can lead to performance regressions, since many applications handle huge pages on their own. Therefore, consider disabling THP. The following steps describe how to disable THP using a Node Tuning Operator (NTO) profile.

3.2.1. Disable THP with a Node Tuning Operator (NTO) profile

Procedure

1. Copy the following NTO sample profile into a YAML file. For example, thp-s390-tuned.yaml:

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
 name: thp-workers-profile
 namespace: openshift-cluster-node-tuning-operator
spec:
 profile:
 - data: |
   [main]
   summary=Custom tuned profile for OpenShift on IBM Z to turn off THP on worker nodes
   include=openshift-node
   [vm]
   transparent_hugepages=never
  name: openshift-thp-never-worker
 recommend:
 - match:
  - label: node-role.kubernetes.io/worker
  priority: 35
  profile: openshift-thp-never-worker
```

2. Create the NTO profile:

\$ oc create -f thp-s390-tuned.yaml

3. Check the list of active profiles:

\$ oc get tuned -n openshift-cluster-node-tuning-operator

4. Remove the profile:

\$ oc delete -f thp-s390-tuned.yaml

Verification

• Log in to one of the nodes and do a regular THP check to verify if the nodes applied the profile successfully:

\$ cat /sys/kernel/mm/transparent_hugepage/enabled always madvise [never]

3.3. BOOST NETWORKING PERFORMANCE WITH RECEIVE FLOW STEERING

Receive Flow Steering (RFS) extends Receive Packet Steering (RPS) by further reducing network latency. RFS is technically based on RPS, and improves the efficiency of packet processing by increasing the CPU cache hit rate. RFS achieves this, and in addition considers queue length, by determining the most convenient CPU for computation so that cache hits are more likely to occur within the CPU. Thus, the CPU cache is invalidated less and requires fewer cycles to rebuild the cache. This can help reduce packet processing run time.

3.3.1. Use the Machine Config Operator (MCO) to activate RFS

Procedure

1. Copy the following MCO sample profile into a YAML file. For example, **enable-rfs.yaml**:

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
  machineconfiguration.openshift.io/role: worker
 name: 50-enable-rfs
spec:
 config:
  ignition:
   version: 2.2.0
  storage:
   files:
   - contents:
     source: data:text/plain;charset=US-
ASCII,%23%20turn%20on%20Receive%20Flow%20Steering%20%28RFS%29%20for%20all
%20network%20interfaces%0ASUBSYSTEM%3D%3D%22net%22%2C%20ACTION%3D%
3D%22add%22%2C%20RUN%7Bprogram%7D%2B%3D%22/bin/bash%20-
c%20%27for%20x%20in%20/sys/%24DEVPATH/queues/rx-
%2A%3B%20do%20echo%208192%20%3E%20%24x/rps flow cnt%3B%20%20done%27
%22%0A
    filesystem: root
    mode: 0644
    path: /etc/udev/rules.d/70-persistent-net.rules
   - contents:
     source: data:text/plain;charset=US-
ASCII,%23%20define%20sock%20flow%20enbtried%20for%20%20Receive%20Flow%20Ste
ering%20%28RFS%29%0Anet.core.rps sock flow entries%3D8192%0A
    filesystem: root
    mode: 0644
    path: /etc/sysctl.d/95-enable-rps.conf
```

2. Create the MCO profile:

\$ oc create -f enable-rfs.yaml

3. Verify that an entry named **50-enable-rfs** is listed:

\$ oc get mc

4. To deactivate, enter:

\$ oc delete mc 50-enable-rfs

Additional resources

- OpenShift Container Platform on IBM Z: Tune your network performance with RFS
- Configuring Receive Flow Steering (RFS)
- Scaling in the Linux Networking Stack

3.4. CHOOSE YOUR NETWORKING SETUP

The networking stack is one of the most important components for a Kubernetes-based product like OpenShift Container Platform. For IBM Z setups, the networking setup depends on the hypervisor of your choice. Depending on the workload and the application, the best fit usually changes with the use case and the traffic pattern.

Depending on your setup, consider these best practices:

- Consider all options regarding networking devices to optimize your traffic pattern. Explore the
 advantages of OSA-Express, RoCE Express, HiperSockets, z/VM VSwitch, Linux Bridge (KVM),
 and others to decide which option leads to the greatest benefit for your setup.
- Always use the latest available NIC version. For example, OSA Express 7S 10 GbE shows great improvement compared to OSA Express 6S 10 GbE with transactional workload types, although both are 10 GbE adapters.
- Each virtual switch adds an additional layer of latency.
- The load balancer plays an important role for network communication outside the cluster. Consider using a production-grade hardware load balancer if this is critical for your application.
- OpenShift Container Platform SDN introduces flows and rules, which impact the networking performance. Make sure to consider pod affinities and placements, to benefit from the locality of services where communication is critical.
- Balance the trade-off between performance and functionality.

Additional resources

- OpenShift Container Platform on IBM Z Performance Experiences, Hints and Tips
- OpenShift Container Platform on IBM Z Networking Performance
- Controlling pod placement on nodes using node affinity rules

3.5. ENSURE HIGH DISK PERFORMANCE WITH HYPERPAV ON Z/VM

DASD and ECKD devices are commonly used disk types in IBM Z environments. In a typical OpenShift Container Platform setup in z/VM environments, DASD disks are commonly used to support the local storage for the nodes. You can set up HyperPAV alias devices to provide more throughput and overall better I/O performance for the DASD disks that support the z/VM guests.

Using HyperPAV for the local storage devices leads to a significant performance benefit. However, you must be aware that there is a trade-off between throughput and CPU costs.

3.5.1. Use the Machine Config Operator (MCO) to activate HyperPAV aliases in nodes using z/VM full-pack minidisks

For z/VM-based OpenShift Container Platform setups that use full-pack minidisks, you can leverage the advantage of MCO profiles by activating HyperPAV aliases in all of the nodes. You must add YAML configurations for both control plane and compute nodes.

Procedure

1. Copy the following MCO sample profile into a YAML file for the control plane node. For example, **05-master-kernelarg-hpav.yaml**:

```
$ cat 05-master-kernelarg-hpav.yaml
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
machineconfiguration.openshift.io/role: master
name: 05-master-kernelarg-hpav
spec:
config:
ignition:
version: 3.1.0
kernelArguments:
- rd.dasd=800-805
```

2. Copy the following MCO sample profile into a YAML file for the compute node. For example, **05-worker-kernelarg-hpav.yaml**:

```
$ cat 05-worker-kernelarg-hpav.yaml
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfig
metadata:
labels:
machineconfiguration.openshift.io/role: worker
name: 05-worker-kernelarg-hpav
spec:
config:
ignition:
version: 3.1.0
kernelArguments:
- rd.dasd=800-805
```



NOTE

You must modify the **rd.dasd** arguments to fit the device IDs.

3. Create the MCO profiles:

\$ oc create -f 05-master-kernelarg-hpav.yaml

\$ oc create -f 05-worker-kernelarg-hpav.yaml

4. To deactivate, enter:

\$ oc delete -f 05-master-kernelarg-hpav.yaml

\$ oc delete -f 05-worker-kernelarg-hpav.yaml

Additional resources

- Using HyperPAV for ECKD DASD
- Scaling HyperPAV alias devices on Linux guests on z/VM

3.6. RHEL KVM ON IBM Z HOST RECOMMENDATIONS

Optimizing a KVM virtual server environment strongly depends on the workloads of the virtual servers and on the available resources. The same action that enhances performance in one environment can have adverse effects in another. Finding the best balance for a particular setting can be a challenge and often involves experimentation.

The following section introduces some best practices when using OpenShift Container Platform with RHEL KVM on IBM Z and LinuxONE environments.

3.6.1. Use multiple queues for your VirtlO network interfaces

With multiple virtual CPUs, you can transfer packages in parallel if you provide multiple queues for incoming and outgoing packets. Use the **queues** attribute of the **driver** element to configure multiple queues. Specify an integer of at least 2 that does not exceed the number of virtual CPUs of the virtual server.

The following example specification configures two input and output queues for a network interface:

```
<interface type="direct">
  <source network="net01"/>
  <model type="virtio"/>
  <driver ... queues="2"/>
  </interface>
```

Multiple queues are designed to provide enhanced performance for a network interface, but they also use memory and CPU resources. Start with defining two queues for busy interfaces. Next, try two queues for interfaces with less traffic or more than two queues for busy interfaces.

3.6.2. Use I/O threads for your virtual block devices

To make virtual block devices use I/O threads, you must configure one or more I/O threads for the virtual server and each virtual block device to use one of these I/O threads.

The following example specifies **<iothreads>3</iothreads>** to configure three I/O threads, with consecutive decimal thread IDs 1, 2, and 3. The **iothread="2"** parameter specifies the driver element of the disk device to use the I/O thread with ID 2.

Sample I/O thread specification

```
...
<domain>
<iothreads>3</iothreads>1
...
<devices>
...
<disk type="block" device="disk">2
<driver ... iothread="2"/>
</disk>
...
</devices>
...
</domain>
```

- The number of I/O threads.
- The driver element of the disk device.

Threads can increase the performance of I/O operations for disk devices, but they also use memory and CPU resources. You can configure multiple devices to use the same thread. The best mapping of threads to devices depends on the available resources and the workload.

Start with a small number of I/O threads. Often, a single I/O thread for all disk devices is sufficient. Do not configure more threads than the number of virtual CPUs, and do not configure idle threads.

You can use the **virsh iothreadadd** command to add I/O threads with specific thread IDs to a running virtual server.

3.6.3. Avoid virtual SCSI devices

Configure virtual SCSI devices only if you need to address the device through SCSI-specific interfaces. Configure disk space as virtual block devices rather than virtual SCSI devices, regardless of the backing on the host.

However, you might need SCSI-specific interfaces for:

- A LUN for a SCSI-attached tape drive on the host.
- A DVD ISO file on the host file system that is mounted on a virtual DVD drive.

3.6.4. Configure guest caching for disk

Configure your disk devices to do caching by the guest and not by the host.

Ensure that the driver element of the disk device includes the **cache="none"** and **io="native"** parameters.

```
<disk type="block" device="disk">
        <driver name="qemu" type="raw" cache="none" io="native" iothread="1"/>
...
</disk>
```

3.6.5. Exclude the memory balloon device

Unless you need a dynamic memory size, do not define a memory balloon device and ensure that libvirt does not create one for you. Include the **memballoon** parameter as a child of the devices element in your domain configuration XML file.

• Check the list of active profiles:

<memballoon model="none"/>

3.6.6. Tune the CPU migration algorithm of the host scheduler



IMPORTANT

Do not change the scheduler settings unless you are an expert who understands the implications. Do not apply changes to production systems without testing them and confirming that they have the intended effect.

The **kernel.sched_migration_cost_ns** parameter specifies a time interval in nanoseconds. After the last execution of a task, the CPU cache is considered to have useful content until this interval expires. Increasing this interval results in fewer task migrations. The default value is 500000 ns.

If the CPU idle time is higher than expected when there are runnable processes, try reducing this interval. If tasks bounce between CPUs or nodes too often, try increasing it.

To dynamically set the interval to 60000 ns, enter the following command:

sysctl kernel.sched_migration_cost_ns=60000

To persistently change the value to 60000 ns, add the following entry to /etc/sysctl.conf:

kernel.sched_migration_cost_ns=60000

3.6.7. Disable the cpuset cgroup controller



NOTE

This setting applies only to KVM hosts with cgroups version 1. To enable CPU hotplug on the host, disable the cgroup controller.

Procedure

- 1. Open /etc/libvirt/qemu.conf with an editor of your choice.
- 2. Go to the **cgroup_controllers** line.
- 3. Duplicate the entire line and remove the leading number sign (#) from the copy.
- 4. Remove the **cpuset** entry, as follows:
 - cgroup_controllers = ["cpu", "devices", "memory", "blkio", "cpuacct"]
- 5. For the new setting to take effect, you must restart the libvirtd daemon:

- a. Stop all virtual machines.
- b. Run the following command:
 - # systemctl restart libvirtd
- c. Restart the virtual machines.

This setting persists across host reboots.

3.6.8. Tune the polling period for idle virtual CPUs

When a virtual CPU becomes idle, KVM polls for wakeup conditions for the virtual CPU before allocating the host resource. You can specify the time interval, during which polling takes place in sysfs at /sys/module/kvm/parameters/halt_poll_ns. During the specified time, polling reduces the wakeup latency for the virtual CPU at the expense of resource usage. Depending on the workload, a longer or shorter time for polling can be beneficial. The time interval is specified in nanoseconds. The default is 50000 ns.

- To optimize for low CPU consumption, enter a small value or write 0 to disable polling:
 - # echo 0 > /sys/module/kvm/parameters/halt_poll_ns
- To optimize for low latency, for example for transactional workloads, enter a large value:
 - # echo 80000 > /sys/module/kvm/parameters/halt_poll_ns

Additional resources

- Linux on IBM Z Performance Tuning for KVM
- Getting started with virtualization on IBM Z

CHAPTER 4. RECOMMENDED CLUSTER SCALING PRACTICES



IMPORTANT

The guidance in this section is only relevant for installations with cloud provider integration.

These guidelines apply to OpenShift Container Platform with software-defined networking (SDN), not Open Virtual Network (OVN).

Apply the following best practices to scale the number of worker machines in your OpenShift Container Platform cluster. You scale the worker machines by increasing or decreasing the number of replicas that are defined in the worker machine set.

4.1. RECOMMENDED PRACTICES FOR SCALING THE CLUSTER

When scaling up the cluster to higher node counts:

- Spread nodes across all of the available zones for higher availability.
- Scale up by no more than 25 to 50 machines at once.
- Consider creating new machine sets in each available zone with alternative instance types of similar size to help mitigate any periodic provider capacity constraints. For example, on AWS, use m5.large and m5d.large.



NOTE

Cloud providers might implement a quota for API services. Therefore, gradually scale the cluster.

The controller might not be able to create the machines if the replicas in the machine sets are set to higher numbers all at one time. The number of requests the cloud platform, which OpenShift Container Platform is deployed on top of, is able to handle impacts the process. The controller will start to query more while trying to create, check, and update the machines with the status. The cloud platform on which OpenShift Container Platform is deployed has API request limits and excessive queries might lead to machine creation failures due to cloud platform limitations.

Enable machine health checks when scaling to large node counts. In case of failures, the health checks monitor the condition and automatically repair unhealthy machines.



NOTE

When scaling large and dense clusters to lower node counts, it might take large amounts of time as the process involves draining or evicting the objects running on the nodes being terminated in parallel. Also, the client might start to throttle the requests if there are too many objects to evict. The default client QPS and burst rates are currently set to 5 and 10 respectively and they cannot be modified in OpenShift Container Platform.

4.2. MODIFYING A MACHINE SET

To make changes to a machine set, edit the **MachineSet** YAML. Then, remove all machines associated with the machine set by deleting each machine or scaling down the machine set to **0** replicas. Then, scale

the replicas back to the desired number. Changes you make to a machine set do not affect existing machines.

If you need to scale a machine set without making other changes, you do not need to delete the machines.



NOTE

By default, the OpenShift Container Platform router pods are deployed on workers. Because the router is required to access some cluster resources, including the web console, do not scale the worker machine set to **0** unless you first relocate the router pods.

Prerequisites

- Install an OpenShift Container Platform cluster and the oc command line.
- Log in to **oc** as a user with **cluster-admin** permission.

Procedure

- 1. Edit the machine set:
 - \$ oc edit machineset <machineset> -n openshift-machine-api
- 2. Scale down the machine set to 0:
 - \$ oc scale --replicas=0 machineset <machineset> -n openshift-machine-api

Or:

\$ oc edit machineset <machineset> -n openshift-machine-api

Wait for the machines to be removed.

- 3. Scale up the machine set as needed:
 - \$ oc scale --replicas=2 machineset <machineset> -n openshift-machine-api

Or:

\$ oc edit machineset <machineset> -n openshift-machine-api

Wait for the machines to start. The new machines contain changes you made to the machine set.

4.3. ABOUT MACHINE HEALTH CHECKS

Machine health checks automatically repair unhealthy machines in a particular machine pool.

To monitor machine health, create a resource to define the configuration for a controller. Set a condition to check, such as staying in the **NotReady** status for five minutes or displaying a permanent condition in the node-problem-detector, and a label for the set of machines to monitor.



NOTE

You cannot apply a machine health check to a machine with the master role.

The controller that observes a **MachineHealthCheck** resource checks for the defined condition. If a machine fails the health check, the machine is automatically deleted and one is created to take its place. When a machine is deleted, you see a **machine deleted** event.

To limit disruptive impact of the machine deletion, the controller drains and deletes only one node at a time. If there are more unhealthy machines than the **maxUnhealthy** threshold allows for in the targeted pool of machines, remediation stops and therefore enables manual intervention.



NOTE

Consider the timeouts carefully, accounting for workloads and requirements.

- Long timeouts can result in long periods of downtime for the workload on the unhealthy machine.
- Too short timeouts can result in a remediation loop. For example, the timeout for checking the **NotReady** status must be long enough to allow the machine to complete the startup process.

To stop the check, remove the resource.

For example, you should stop the check during the upgrade process because the nodes in the cluster might become temporarily unavailable. The **MachineHealthCheck** might identify such nodes as unhealthy and reboot them. To avoid rebooting such nodes, remove any **MachineHealthCheck** resource that you have deployed before updating the cluster. However, a **MachineHealthCheck** resource that is deployed by default (such as **machine-api-termination-handler**) cannot be removed and will be recreated.

4.3.1. Limitations when deploying machine health checks

There are limitations to consider before deploying a machine health check:

- Only machines owned by a machine set are remediated by a machine health check.
- Control plane machines are not currently supported and are not remediated if they are unhealthy.
- If the node for a machine is removed from the cluster, a machine health check considers the machine to be unhealthy and remediates it immediately.
- If the corresponding node for a machine does not join the cluster after the **nodeStartupTimeout**, the machine is remediated.
- A machine is remediated immediately if the Machine resource phase is Failed.

4.4. SAMPLE MACHINEHEALTHCHECK RESOURCE

The **MachineHealthCheck** resource for all cloud-based installation types, and other than bare metal, resembles the following YAML file:

apiVersion: machine.openshift.io/v1beta1 kind: MachineHealthCheck metadata: name: example 1 namespace: openshift-machine-api spec: selector: matchLabels: machine.openshift.io/cluster-api-machine-role: <role> 2 machine.openshift.io/cluster-api-machine-type: <role> 3 machine.openshift.io/cluster-api-machineset: <cluster name>-<label>-<zone> 4 unhealthyConditions: "Ready" type: timeout: "300s" 5 status: "False" - type: "Ready" timeout: "300s" 6 status: "Unknown" maxUnhealthy: "40%" 7 nodeStartupTimeout: "10m" (8)

- Specify the name of the machine health check to deploy.
- 23 Specify a label for the machine pool that you want to check.
- 4 Specify the machine set to track in **<cluster_name>-<label>-<zone>** format. For example, **prod-node-us-east-1a**.
- Specify the timeout duration for a node condition. If a condition is met for the duration of the timeout, the machine will be remediated. Long timeouts can result in long periods of downtime for a workload on an unhealthy machine.
- Specify the amount of machines allowed to be concurrently remediated in the targeted pool. This can be set as a percentage or an integer. If the number of unhealthy machines exceeds the limit set by **maxUnhealthy**, remediation is not performed.
- 8 Specify the timeout duration that a machine health check must wait for a node to join the cluster before a machine is determined to be unhealthy.



NOTE

The **matchLabels** are examples only; you must map your machine groups based on your specific needs.

4.4.1. Short-circuiting machine health check remediation

Short circuiting ensures that machine health checks remediate machines only when the cluster is healthy. Short-circuiting is configured through the **maxUnhealthy** field in the **MachineHealthCheck** resource.

If the user defines a value for the **maxUnhealthy** field, before remediating any machines, the **MachineHealthCheck** compares the value of **maxUnhealthy** with the number of machines within its target pool that it has determined to be unhealthy. Remediation is not performed if the number of

unhealthy machines exceeds the **maxUnhealthy** limit.



IMPORTANT

If **maxUnhealthy** is not set, the value defaults to **100%** and the machines are remediated regardless of the state of the cluster.

The appropriate **maxUnhealthy** value depends on the scale of the cluster you deploy and how many machines the **MachineHealthCheck** covers. For example, you can use the **maxUnhealthy** value to cover multiple machine sets across multiple availability zones so that if you lose an entire zone, your **maxUnhealthy** setting prevents further remediation within the cluster.

The **maxUnhealthy** field can be set as either an integer or percentage. There are different remediation implementations depending on the **maxUnhealthy** value.

4.4.1.1. Setting maxUnhealthy by using an absolute value

If maxUnhealthy is set to 2:

- Remediation will be performed if 2 or fewer nodes are unhealthy
- Remediation will not be performed if 3 or more nodes are unhealthy

These values are independent of how many machines are being checked by the machine health check.

4.4.1.2. Setting maxUnhealthy by using percentages

If **maxUnhealthy** is set to **40%** and there are 25 machines being checked:

- Remediation will be performed if 10 or fewer nodes are unhealthy
- Remediation will not be performed if 11 or more nodes are unhealthy

If **maxUnhealthy** is set to **40%** and there are 6 machines being checked:

- Remediation will be performed if 2 or fewer nodes are unhealthy
- Remediation will not be performed if 3 or more nodes are unhealthy



NOTE

The allowed number of machines is rounded down when the percentage of **maxUnhealthy** machines that are checked is not a whole number.

4.5. CREATING A MACHINEHEALTHCHECK RESOURCE

You can create a **MachineHealthCheck** resource for all **MachineSets** in your cluster. You should not create a **MachineHealthCheck** resource that targets control plane machines.

Prerequisites

• Install the **oc** command line interface.

Procedure

- 1. Create a **healthcheck.yml** file that contains the definition of your machine health check.
- 2. Apply the **healthcheck.yml** file to your cluster:

\$ oc apply -f healthcheck.yml

CHAPTER 5. USING THE NODE TUNING OPERATOR

Learn about the Node Tuning Operator and how you can use it to manage node-level tuning by orchestrating the tuned daemon.

5.1. ABOUT THE NODE TUNING OPERATOR

The Node Tuning Operator helps you manage node-level tuning by orchestrating the TuneD daemon. The majority of high-performance applications require some level of kernel tuning. The Node Tuning Operator provides a unified management interface to users of node-level sysctls and more flexibility to add custom tuning specified by user needs.

The Operator manages the containerized TuneD daemon for OpenShift Container Platform as a Kubernetes daemon set. It ensures the custom tuning specification is passed to all containerized TuneD daemons running in the cluster in the format that the daemons understand. The daemons run on all nodes in the cluster, one per node.

Node-level settings applied by the containerized TuneD daemon are rolled back on an event that triggers a profile change or when the containerized TuneD daemon is terminated gracefully by receiving and handling a termination signal.


The Node Tuning Operator is part of a standard OpenShift Container Platform installation in version 4.1 and later.

5.2. ACCESSING AN EXAMPLE NODE TUNING OPERATOR SPECIFICATION

Use this process to access an example Node Tuning Operator specification.

Procedure

1. Run:



The default CR is meant for delivering standard node-level tuning for the OpenShift Container Platform platform and it can only be modified to set the Operator Management state. Any other custom changes to the default CR will be overwritten by the Operator. For custom tuning, create your own Tuned CRs. Newly created CRs will be combined with the default CR and custom tuning applied to OpenShift Container Platform nodes based on node or pod labels and profile priorities.



WARNING

While in certain situations the support for pod labels can be a convenient way of automatically delivering required tuning, this practice is discouraged and strongly advised against, especially in large-scale clusters. The default Tuned CR ships without pod label matching. If a custom profile is created with pod label matching, then the functionality will be enabled at that time. The pod label functionality might be deprecated in future versions of the Node Tuning Operator.

5.3. DEFAULT PROFILES SET ON A CLUSTER

The following are the default profiles set on a cluster.

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
 name: default
 namespace: openshift-cluster-node-tuning-operator
spec:
 profile:
 - name: "openshift"
  data: |
   [main]
   summary=Optimize systems running OpenShift (parent profile)
   include=${f:virt_check:virtual-guest:throughput-performance}
   [selinux]
   avc cache threshold=8192
   [net]
   nf conntrack hashsize=131072
   [sysctl]
   net.ipv4.ip_forward=1
   kernel.pid max=>4194304
   net.netfilter.nf conntrack max=1048576
   net.ipv4.conf.all.arp_announce=2
   net.ipv4.neigh.default.gc_thresh1=8192
   net.ipv4.neigh.default.gc thresh2=32768
   net.ipv4.neigh.default.gc thresh3=65536
   net.ipv6.neigh.default.gc thresh1=8192
   net.ipv6.neigh.default.gc_thresh2=32768
   net.ipv6.neigh.default.gc_thresh3=65536
   vm.max map count=262144
   [sysfs]
   /sys/module/nvme_core/parameters/io_timeout=4294967295
   /sys/module/nvme core/parameters/max retries=10
 - name: "openshift-control-plane"
  data: |
   [main]
   summary=Optimize systems running OpenShift control plane
   include=openshift
   [sysctl]
   # ktune sysctl settings, maximizing i/o throughput
   # Minimal preemption granularity for CPU-bound tasks:
   # (default: 1 msec# (1 + ilog(ncpus)), units: nanoseconds)
   kernel.sched_min_granularity_ns=10000000
   # The total time the scheduler will consider a migrated process
   # "cache hot" and thus less likely to be re-migrated
   # (system default is 500000, i.e. 0.5 ms)
   kernel.sched_migration_cost_ns=5000000
```

```
# SCHED_OTHER wake-up granularity.
  # Preemption granularity when tasks wake up. Lower the value to
  # improve wake-up latency and throughput for latency critical tasks.
  kernel.sched wakeup granularity ns=4000000
- name: "openshift-node"
 data: |
  [main]
  summary=Optimize systems running OpenShift nodes
  include=openshift
  [sysctl]
  net.ipv4.tcp_fastopen=3
  fs.inotify.max_user_watches=65536
  fs.inotify.max_user_instances=8192
recommend:
- profile: "openshift-control-plane"
 priority: 30
 match:
 - label: "node-role.kubernetes.io/master"
 - label: "node-role.kubernetes.io/infra"
- profile: "openshift-node"
 priority: 40
```

5.4. VERIFYING THAT THE TUNED PROFILES ARE APPLIED

Starting with OpenShift Container Platform 4.8, it is no longer necessary to check the TuneD pod logs to find which TuneD profiles are applied on cluster nodes.

\$ oc get profile -n openshift-cluster-node-tuning-operator

Example output

NAME	TUNED	ΑP	PLIED	DEGR.	ADED	AGE
master-0	openshift-control-pla	ane	True	False	6h3	3m
master-1	openshift-control-pla	ane	True	False	6h3	3m
master-2	openshift-control-pla	ane	True	False	6h3	3m
worker-a	openshift-node	Т	rue	False	6h28n	1
worker-b	openshift-node	Т	rue	False	6h28n	า

- **NAME**: Name of the Profile object. There is one Profile object per node and their names match.
- TUNED: Name of the desired TuneD profile to apply.
- APPLIED: True if the TuneD daemon applied the desired profile. (True/False/Unknown).
- **DEGRADED**: **True** if any errors were reported during application of the TuneD profile (**True/False/Unknown**).
- AGE: Time elapsed since the creation of Profile object.

5.5. CUSTOM TUNING SPECIFICATION

The custom resource (CR) for the Operator has two major sections. The first section, **profile:**, is a list of TuneD profiles and their names. The second, **recommend:**, defines the profile selection logic.

Multiple custom tuning specifications can co-exist as multiple CRs in the Operator's namespace. The existence of new CRs or the deletion of old CRs is detected by the Operator. All existing custom tuning specifications are merged and appropriate objects for the containerized TuneD daemons are updated.

Management state

The Operator Management state is set by adjusting the default Tuned CR. By default, the Operator is in the Managed state and the **spec.managementState** field is not present in the default Tuned CR. Valid values for the Operator Management state are as follows:

- Managed: the Operator will update its operands as configuration resources are updated
- Unmanaged: the Operator will ignore changes to the configuration resources
- Removed: the Operator will remove its operands and resources the Operator provisioned

Profile data

The **profile:** section lists TuneD profiles and their names.

```
profile:
- name: tuned_profile_1
data: |
# TuneD profile specification
[main]
summary=Description of tuned_profile_1 profile

[sysctl]
net.ipv4.ip_forward=1
# ... other sysctl's or other TuneD daemon plugins supported by the containerized TuneD

# ...
- name: tuned_profile_n
data: |
# TuneD profile specification
[main]
summary=Description of tuned_profile_n profile

# tuned_profile_n profile settings
```

Recommended profiles

The **profile:** selection logic is defined by the **recommend:** section of the CR. The **recommend:** section is a list of items to recommend the profiles based on a selection criteria.

```
recommend:
<recommend-item-1>
# ...
<recommend-item-n>
```

The individual items of the list:

```
- machineConfigLabels: 1
    <mcLabels> 2
    match: 3
    <match> 4
    priority: <priority> 5
    profile: <tuned_profile_name> 6
```

- Optional.
- A dictionary of key/value **MachineConfig** labels. The keys must be unique.
- If omitted, profile match is assumed unless a profile with a higher priority matches first or **machineConfigLabels** is set.
- An optional list.
- 5 Profile ordering priority. Lower numbers mean higher priority (**0** is the highest priority).
- A TuneD profile to apply on a match. For example tuned_profile_1.

<match> is an optional list recursively defined as follows:

```
- label: <label_name> 1
value: <label_value> 2
type: <label_type> 3
<match> 4
```

- Node or pod label name.
- Optional node or pod label value. If omitted, the presence of **<label_name>** is enough to match.
- Optional object type (**node** or **pod**). If omitted, **node** is assumed.
- An optional <match> list.

If <match> is not omitted, all nested <match> sections must also evaluate to true. Otherwise, false is assumed and the profile with the respective <match> section will not be applied or recommended. Therefore, the nesting (child <match> sections) works as logical AND operator. Conversely, if any item of the <match> list matches, the entire <match> list evaluates to true. Therefore, the list acts as logical OR operator.

If machineConfigLabels is defined, machine config pool based matching is turned on for the given recommend: list item. <mcLabels> specifies the labels for a machine config. The machine config is created automatically to apply host settings, such as kernel boot parameters, for the profile <tuned_profile_name>. This involves finding all machine config pools with machine config selector matching <mcLabels> and setting the profile <tuned_profile_name> on all nodes that are assigned the found machine config pools. To target nodes that have both master and worker roles, you must use the master role.

The list items **match** and **machineConfigLabels** are connected by the logical OR operator. The **match** item is evaluated first in a short-circuit manner. Therefore, if it evaluates to **true**, the **machineConfigLabels** item is not considered.



IMPORTANT

When using machine config pool based matching, it is advised to group nodes with the same hardware configuration into the same machine config pool. Not following this practice might result in TuneD operands calculating conflicting kernel parameters for two or more nodes sharing the same machine config pool.

Example: node or pod label based matching

- match:
- label: tuned.openshift.io/elasticsearch match:
 - label: node-role.kubernetes.io/master
 label: node-role.kubernetes.io/infra type: pod

priority: 10

profile: openshift-control-plane-es

- match:
 - label: node-role.kubernetes.io/masterlabel: node-role.kubernetes.io/infra

priority: 20

profile: openshift-control-plane


- priority: 30

profile: openshift-node

The CR above is translated for the containerized TuneD daemon into its **recommend.conf** file based on the profile priorities. The profile with the highest priority (10) is **openshift-control-plane-es** and, therefore, it is considered first. The containerized TuneD daemon running on a given node looks to see if there is a pod running on the same node with the **tuned.openshift.io/elasticsearch** label set. If not, the entire **<match>** section evaluates as **false**. If there is such a pod with the label, in order for the **<match>** section to evaluate to **true**, the node label also needs to be **node-role.kubernetes.io/master** or **node-role.kubernetes.io/infra**.

If the labels for the profile with priority **10** matched, **openshift-control-plane-es** profile is applied and no other profile is considered. If the node/pod label combination did not match, the second highest priority profile (**openshift-control-plane**) is considered. This profile is applied if the containerized TuneD pod runs on a node with labels **node-role.kubernetes.io/master** or **node-role.kubernetes.io/infra**.

Finally, the profile **openshift-node** has the lowest priority of **30**. It lacks the **<match>** section and, therefore, will always match. It acts as a profile catch-all to set **openshift-node** profile, if no other profile with higher priority matches on a given node.



OPENSHIFT_10_0319

Example: machine config pool based matching

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
 name: openshift-node-custom
 namespace: openshift-cluster-node-tuning-operator
spec:
 profile:
 - data: |
   [main]
   summary=Custom OpenShift node profile with an additional kernel parameter
   include=openshift-node
   [bootloader]
   cmdline_openshift_node_custom=+skew_tick=1
  name: openshift-node-custom
 recommend:
 - machineConfigLabels:
   machineconfiguration.openshift.io/role: "worker-custom"
  priority: 20
  profile: openshift-node-custom
```

To minimize node reboots, label the target nodes with a label the machine config pool's node selector will match, then create the Tuned CR above and finally create the custom machine config pool itself.

5.6. CUSTOM TUNING EXAMPLES

Using TuneD profiles from the default CR

The following CR applies custom node-level tuning for OpenShift Container Platform nodes with label **tuned.openshift.io/ingress-node-label** set to any value.

Example: custom tuning using the openshift-control-plane TuneD profile

apiVersion: tuned.openshift.io/v1 kind: Tuned metadata: name: ingress namespace: openshift-cluster-node-tuning-operator profile: - data: | [main] summary=A custom OpenShift ingress profile include=openshift-control-plane [sysctl] net.ipv4.ip local port range="1024 65535" net.ipv4.tcp tw reuse=1 name: openshift-ingress recommend: - match: - label: tuned.openshift.io/ingress-node-label priority: 10 profile: openshift-ingress



IMPORTANT

Custom profile writers are strongly encouraged to include the default TuneD daemon profiles shipped within the default Tuned CR. The example above uses the default **openshift-control-plane** profile to accomplish this.

Using built-in TuneD profiles

Given the successful rollout of the NTO-managed daemon set, the TuneD operands all manage the same version of the TuneD daemon. To list the built-in TuneD profiles supported by the daemon, query any TuneD pod in the following way:

 $\$ oc exec $\$ tuned_pod -n openshift-cluster-node-tuning-operator -- find /usr/lib/tuned/ -name tuned.conf -printf '%h\n' | sed 's|^.*/||'

You can use the profile names retrieved by this in your custom tuning specification.

Example: using built-in hpc-compute TuneD profile

apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
name: openshift-node-hpc-compute
namespace: openshift-cluster-node-tuning-operator
spec:
profile:

- data: | [main]

summary=Custom OpenShift node profile for HPC compute workloads include=openshift-node,hpc-compute

name: openshift-node-hpc-compute

recommend:

- match:

- label: tuned.openshift.io/openshift-node-hpc-compute

priority: 20

profile: openshift-node-hpc-compute

In addition to the built-in **hpc-compute** profile, the example above includes the **openshift-node** TuneD daemon profile shipped within the default Tuned CR to use OpenShift-specific tuning for compute nodes

5.7. SUPPORTED TUNED DAEMON PLUG-INS

Excluding the **[main]** section, the following TuneD plug-ins are supported when using custom profiles defined in the **profile:** section of the Tuned CR:

- audio
- cpu
- disk
- eeepc_she
- modules
- mounts
- net
- scheduler
- scsi host
- selinux
- sysctl
- sysfs
- usb
- video
- vm

There is some dynamic tuning functionality provided by some of these plug-ins that is not supported. The following TuneD plug-ins are currently not supported:

- bootloader
- script

systemd

See Available TuneD Plug-ins and Getting Started with TuneD for more information.

CHAPTER 6. USING CLUSTER LOADER

Cluster Loader is a tool that deploys large numbers of various objects to a cluster, which creates user-defined cluster objects. Build, configure, and run Cluster Loader to measure performance metrics of your OpenShift Container Platform deployment at various cluster states.



IMPORTANT

Cluster Loader is now deprecated and will be removed in a future release.

6.1. INSTALLING CLUSTER LOADER

Procedure

1. To pull the container image, run:

\$ podman pull quay.io/openshift/origin-tests:4.8

6.2. RUNNING CLUSTER LOADER

Prerequisites

 The repository will prompt you to authenticate. The registry credentials allow you to access the image, which is not publicly available. Use your existing authentication credentials from installation.

Procedure

1. Execute Cluster Loader using the built-in test configuration, which deploys five template builds and waits for them to complete:

 $\label{lem:config} $$ podman run -v $\{LOCAL_KUBECONFIG\}:/root/.kube/config:z -i \land quay.io/openshift/origin-tests:4.8 /bin/bash -c 'export KUBECONFIG=/root/.kube/config && \land openshift-tests run-test "[sig-scalability][Feature:Performance] Load cluster $$ should populate the cluster [Slow][Serial] [Suite:openshift]"' $$$

Alternatively, execute Cluster Loader with a user-defined configuration by setting the environment variable for **VIPERCONFIG**:

\$ podman run -v \${LOCAL_KUBECONFIG}:/root/.kube/config:z \
-v \${LOCAL_CONFIG_FILE_PATH}:/root/configs/:z \
-i quay.io/openshift/origin-tests:4.8 \
/bin/bash -c 'KUBECONFIG=/root/.kube/config VIPERCONFIG=/root/configs/test.yaml \
openshift-tests run-test "[sig-scalability][Feature:Performance] Load cluster \
should populate the cluster [Slow][Serial] [Suite:openshift]"'

In this example, **\${LOCAL_KUBECONFIG}** refers to the path to the **kubeconfig** on your local file system. Also, there is a directory called **\${LOCAL_CONFIG_FILE_PATH}**, which is mounted into the container that contains a configuration file called **test.yaml**. Additionally, if the **test.yaml** references any external template files or podspec files, they should also be mounted into the container.

6.3. CONFIGURING CLUSTER LOADER

The tool creates multiple namespaces (projects), which contain multiple templates or pods.

6.3.1. Example Cluster Loader configuration file

Cluster Loader's configuration file is a basic YAML file:

```
provider: local 1
ClusterLoader:
 cleanup: true
 projects:
  - num: 1
   basename: clusterloader-cakephp-mysql
   tuning: default
   ifexists: reuse
   templates:
    - num: 1
      file: cakephp-mysql.json
  - num: 1
   basename: clusterloader-dancer-mysql
   tuning: default
   ifexists: reuse
   templates:
    - num: 1
      file: dancer-mysql.json
  - num: 1
   basename: clusterloader-django-postgresql
   tuning: default
   ifexists: reuse
   templates:
     - num: 1
      file: django-postgresql.json
  - num: 1
   basename: clusterloader-nodejs-mongodb
   tuning: default
   ifexists: reuse
   templates:
    - num: 1
      file: quickstarts/nodejs-mongodb.json
  - num: 1
   basename: clusterloader-rails-postgresql
   tuning: default
   templates:
     - num: 1
      file: rails-postgresql.json
 tuningsets: 2
  - name: default
   pods:
     stepping: 3
```

stepsize: 5 pause: 0 s rate_limit: 4 delay: 0 ms

- Optional setting for end-to-end tests. Set to **local** to avoid extra log messages.
- The tuning sets allow rate limiting and stepping, the ability to create several batches of pods while pausing in between sets. Cluster Loader monitors completion of the previous step before continuing.
- Stepping will pause for **M** seconds after each **N** objects are created.
- Rate limiting will wait M milliseconds between the creation of objects.

This example assumes that references to any external template files or pod spec files are also mounted into the container.



IMPORTANT

If you are running Cluster Loader on Microsoft Azure, then you must set the **AZURE_AUTH_LOCATION** variable to a file that contains the output of **terraform.azure.auto.tfvars.json**, which is present in the installer directory.

6.3.2. Configuration fields

Table 6.1. Top-level Cluster Loader Fields

Field	Description
cleanup	Set to true or false . One definition per configuration. If set to true , cleanup deletes all namespaces (projects) created by Cluster Loader at the end of the test.
projects	A sub-object with one or many definition(s). Under projects , each namespace to create is defined and projects has several mandatory subheadings.
tuningsets	A sub-object with one definition per configuration. tuningsets allows the user to define a tuning set to add configurable timing to project or object creation (pods, templates, and so on).
sync	An optional sub-object with one definition per configuration. Adds synchronization possibilities during object creation.

Table 6.2. Fields under **projects**

Field	Description
num	An integer. One definition of the count of how many projects to create.
basename	A string. One definition of the base name for the project. The count of identical namespaces will be appended to Basename to prevent collisions.
tuning	A string. One definition of what tuning set you want to apply to the objects, which you deploy inside this namespace.
ifexists	A string containing either reuse or delete . Defines what the tool does if it finds a project or namespace that has the same name of the project or namespace it creates during execution.
configmaps	A list of key-value pairs. The key is the config map name and the value is a path to a file from which you create the config map.
secrets	A list of key-value pairs. The key is the secret name and the value is a path to a file from which you create the secret.
pods	A sub-object with one or many definition(s) of pods to deploy.
templates	A sub-object with one or many definition(s) of templates to deploy.

Table 6.3. Fields under pods and templates

Field	Description
num	An integer. The number of pods or templates to deploy.
image	A string. The docker image URL to a repository where it can be pulled.
basename	A string. One definition of the base name for the template (or pod) that you want to create.
file	A string. The path to a local file, which is either a pod spec or template to be created.

Field	Description		
parameters	Key-value pairs. Under parameters , you can specify a list of values to override in the pod or template.		

Table 6.4. Fields under tuningsets

Field	Description
name	A string. The name of the tuning set which will match the name specified when defining a tuning in a project.
pods	A sub-object identifying the tuningsets that will apply to pods.
templates	A sub-object identifying the tuningsets that will apply to templates.

Table 6.5. Fields under tuningsets pods or tuningsets templates

Field	Description
stepping	A sub-object. A stepping configuration used if you want to create an object in a step creation pattern.
rate_limit	A sub-object. A rate-limiting tuning set configuration to limit the object creation rate.

Table 6.6. Fields under tuningsets pods or tuningsets templates, stepping

Field	Description
stepsize	An integer. How many objects to create before pausing object creation.
pause	An integer. How many seconds to pause after creating the number of objects defined in stepsize .
timeout	An integer. How many seconds to wait before failure if the object creation is not successful.
delay	An integer. How many milliseconds (ms) to wait between creation requests.

Table 6.7. Fields under **sync**

Field	Description
server	A sub-object with enabled and port fields. The boolean enabled defines whether to start an HTTP server for pod synchronization. The integer port defines the HTTP server port to listen on (9090 by default).
running	A boolean. Wait for pods with labels matching selectors to go into Running state.
succeeded	A boolean. Wait for pods with labels matching selectors to go into Completed state.
selectors	A list of selectors to match pods in Running or Completed states.
timeout	A string. The synchronization timeout period to wait for pods in Running or Completed states. For values that are not 0 , use units: [ns us ms s m h].

6.4. KNOWN ISSUES

- Cluster Loader fails when called without configuration. (BZ#1761925)
- If the **IDENTIFIER** parameter is not defined in user templates, template creation fails with **error: unknown parameter name "IDENTIFIER"**. If you deploy templates, add this parameter to your template to avoid this error:

```
{
    "name": "IDENTIFIER",
    "description": "Number to append to the name of resources",
    "value": "1"
}
```

If you deploy pods, adding the parameter is unnecessary.

CHAPTER 7. USING CPU MANAGER

CPU Manager manages groups of CPUs and constrains workloads to specific CPUs.

CPU Manager is useful for workloads that have some of these attributes:

- Require as much CPU time as possible.
- Are sensitive to processor cache misses.
- Are low-latency network applications.
- Coordinate with other processes and benefit from sharing a single processor cache.

7.1. SETTING UP CPU MANAGER

Procedure

1. Optional: Label a node:

oc label node perf-node.example.com cpumanager=true

- 2. Edit the **MachineConfigPool** of the nodes where CPU Manager should be enabled. In this example, all workers have CPU Manager enabled:
 - # oc edit machineconfigpool worker
- 3. Add a label to the worker machine config pool:

metadata: creationTimestamp: 2020-xx-xxx generation: 3 labels:

custom-kubelet: cpumanager-enabled

4. Create a **KubeletConfig**, **cpumanager-kubeletconfig.yaml**, custom resource (CR). Refer to the label created in the previous step to have the correct nodes updated with the new kubelet config. See the **machineConfigPoolSelector** section:

apiVersion: machineconfiguration.openshift.io/v1 kind: KubeletConfig metadata: name: cpumanager-enabled spec: machineConfigPoolSelector: matchLabels: custom-kubelet: cpumanager-enabled kubeletConfig: cpuManagerPolicy: static 1

cpuManagerReconcilePeriod: 5s 2

Specify a policy:

- **none**. This policy explicitly enables the existing default CPU affinity scheme, providing no affinity beyond what the scheduler does automatically.
- **static**. This policy allows pods with certain resource characteristics to be granted increased CPU affinity and exclusivity on the node.
- Optional. Specify the CPU Manager reconcile frequency. The default is **5s**.
- 5. Create the dynamic kubelet config:
 - # oc create -f cpumanager-kubeletconfig.yaml

This adds the CPU Manager feature to the kubelet config and, if needed, the Machine Config Operator (MCO) reboots the node. To enable CPU Manager, a reboot is not needed.

6. Check for the merged kubelet config:

oc get machineconfig 99-worker-XXXXXX-XXXXX-XXXXX-kubelet -o json | grep ownerReference -A7

Example output

7. Check the worker for the updated **kubelet.conf**:

oc debug node/perf-node.example.com sh-4.2# cat /host/etc/kubernetes/kubelet.conf | grep cpuManager

Example output

cpuManagerPolicy: static cpuManagerReconcilePeriod: 5s 2

- 12 These settings were defined when you created the **KubeletConfig** CR.
- 8. Create a pod that requests a core or multiple cores. Both limits and requests must have their CPU value set to a whole integer. That is the number of cores that will be dedicated to this pod:
 - # cat cpumanager-pod.yaml

Example output

apiVersion: v1

```
kind: Pod
metadata:
 generateName: cpumanager-
spec:
 containers:
 - name: cpumanager
  image: gcr.io/google containers/pause-amd64:3.0
  resources:
   requests:
    cpu: 1
    memory: "1G"
   limits:
    cpu: 1
    memory: "1G"
 nodeSelector:
  cpumanager: "true"
```

9. Create the pod:

oc create -f cpumanager-pod.yaml

10. Verify that the pod is scheduled to the node that you labeled:

oc describe pod cpumanager

Example output

```
Name:
              cpumanager-6cqz7
                default
Namespace:
Priority:
            0
PriorityClassName: <none>
Node: perf-node.example.com/xxx.xx.xx.xxx
Limits:
   cpu:
        1
   memory: 1G
  Requests:
   cpu:
   memory: 1G
QoS Class:
             Guaranteed
Node-Selectors: cpumanager=true
```

11. Verify that the **cgroups** are set up correctly. Get the process ID (PID) of the **pause** process:

Pods of quality of service (QoS) tier **Guaranteed** are placed within the **kubepods.slice**. Pods of other QoS tiers end up in child **cgroups** of **kubepods**:

cd /sys/fs/cgroup/cpuset/kubepods.slice/kubepods-pod69c01f8e_6b74_11e9_ac0f_0a2b62178a22.slice/crio-b5437308f1ad1a7db0574c542bdf08563b865c0345c86e9585f8c0b0a655612c.scope # for i in `ls cpuset.cpus tasks`; do echo -n "\$i "; cat \$i ; done

Example output

cpuset.cpus 1 tasks 32706

12. Check the allowed CPU list for the task:

grep ^Cpus_allowed_list /proc/32706/status

Example output

Cpus_allowed_list: 1

13. Verify that another pod (in this case, the pod in the **burstable** QoS tier) on the system cannot run on the core allocated for the **Guaranteed** pod:

cat /sys/fs/cgroup/cpuset/kubepods.slice/kubepods-besteffort.slice/kubepods-besteffort-podc494a073_6b77_11e9_98c0_06bba5c387ea.slice/crio-c56982f57b75a2420947f0afc6cafe7534c5734efc34157525fa9abbf99e3849.scope/cpuset.cpus

0

oc describe node perf-node.example.com

Example output

Allocated resources:

Capacity: attachable-volumes-aws-ebs: 39 ephemeral-storage: 124768236Ki hugepages-1Gi: 0 hugepages-2Mi: 0 memory: 8162900Ki pods: 250 Allocatable: attachable-volumes-aws-ebs: 39 1500m ephemeral-storage: 124768236Ki 0 hugepages-1Gi: hugepages-2Mi: memory: 7548500Ki pods: 250 default cpumanager-6cqz7 1 (66%) 1 (66%) 1G (12%) 1G (12%) 29m

```
(Total limits may be over 100 percent, i.e., overcommitted.)
Resource Requests Limits
------
cpu 1440m (96%) 1 (66%)
```

This VM has two CPU cores. The **system-reserved** setting reserves 500 millicores, meaning that half of one core is subtracted from the total capacity of the node to arrive at the **Node Allocatable** amount. You can see that **Allocatable CPU** is 1500 millicores. This means you can run one of the CPU Manager pods since each will take one whole core. A whole core is equivalent to 1000 millicores. If you try to schedule a second pod, the system will accept the pod, but it will never be scheduled:

NAME	READY	STATUS	RES	TARTS	AGE
cpumanager-6cqz	7 1/1	Running	0	33m	
cpumanager-7qc2	t 0/1	Pending	0	11s	

CHAPTER 8. USING TOPOLOGY MANAGER

Topology Manager collects hints from the CPU Manager, Device Manager, and other Hint Providers to align pod resources, such as CPU, SR-IOV VFs, and other device resources, for all Quality of Service (QoS) classes on the same non-uniform memory access (NUMA) node.

Topology Manager uses topology information from collected hints to decide if a pod can be accepted or rejected on a node, based on the configured Topology Manager policy and Pod resources requested.

Topology Manager is useful for workloads that use hardware accelerators to support latency-critical execution and high throughput parallel computation.



NOTE

To use Topology Manager you must use the CPU Manager with the **static** policy. For more information on CPU Manager, see Using CPU Manager.

8.1. TOPOLOGY MANAGER POLICIES

Topology Manager aligns **Pod** resources of all Quality of Service (QoS) classes by collecting topology hints from Hint Providers, such as CPU Manager and Device Manager, and using the collected hints to align the **Pod** resources.



NOTE

To align CPU resources with other requested resources in a **Pod** spec, the CPU Manager must be enabled with the **static** CPU Manager policy.

Topology Manager supports four allocation policies, which you assign in the **cpumanager-enabled** custom resource (CR):

none policy

This is the default policy and does not perform any topology alignment.

best-effort policy

For each container in a pod with the **best-effort** topology management policy, kubelet calls each Hint Provider to discover their resource availability. Using this information, the Topology Manager stores the preferred NUMA Node affinity for that container. If the affinity is not preferred, Topology Manager stores this and admits the pod to the node.

restricted policy

For each container in a pod with the **restricted** topology management policy, kubelet calls each Hint Provider to discover their resource availability. Using this information, the Topology Manager stores the preferred NUMA Node affinity for that container. If the affinity is not preferred, Topology Manager rejects this pod from the node, resulting in a pod in a **Terminated** state with a pod admission failure.

single-numa-node policy

For each container in a pod with the **single-numa-node** topology management policy, kubelet calls each Hint Provider to discover their resource availability. Using this information, the Topology Manager determines if a single NUMA Node affinity is possible. If it is, the pod is admitted to the node. If a single NUMA Node affinity is not possible, the Topology Manager rejects the pod from the node. This results in a pod in a Terminated state with a pod admission failure.

8.2. SETTING UP TOPOLOGY MANAGER

To use Topology Manager, you must configure an allocation policy in the **cpumanager-enabled** custom resource (CR). This file might exist if you have set up CPU Manager. If the file does not exist, you can create the file.

Prequisites

• Configure the CPU Manager policy to be **static**. See the Using CPU Manager in the Scalability and Performance section.

Procedure

To activate Topololgy Manager:

 Configure the Topology Manager allocation policy in the cpumanager-enabled custom resource (CR).

\$ oc edit KubeletConfig cpumanager-enabled

apiVersion: machineconfiguration.openshift.io/v1

kind: KubeletConfig

metadata:

name: cpumanager-enabled

spec:

machineConfigPoolSelector:

matchLabels:

custom-kubelet: cpumanager-enabled

kubeletConfig:

cpuManagerPolicy: static 1 cpuManagerReconcilePeriod: 5s

topologyManagerPolicy: single-numa-node 2

- 1 This parameter must be **static**.
- Specify your selected Topology Manager allocation policy. Here, the policy is single-numa-node. Acceptable values are: default, best-effort, restricted, single-numa-node.

Additional resources

For more information on CPU Manager, see Using CPU Manager.

8.3. POD INTERACTIONS WITH TOPOLOGY MANAGER POLICIES

The example **Pod** specs below help illustrate pod interactions with Topology Manager.

The following pod runs in the **BestEffort** QoS class because no resource requests or limits are specified.

spec:

containers:

name: nginx image: nginx

The next pod runs in the **Burstable** QoS class because requests are less than limits.

```
spec:
containers:
- name: nginx
image: nginx
resources:
limits:
memory: "200Mi"
requests:
memory: "100Mi"
```

If the selected policy is anything other than **none**, Topology Manager would not consider either of these **Pod** specifications.

The last example pod below runs in the Guaranteed QoS class because requests are equal to limits.

```
spec:
containers:
- name: nginx
image: nginx
resources:
limits:
memory: "200Mi"
cpu: "2"
example.com/device: "1"
requests:
memory: "200Mi"
cpu: "2"
example.com/device: "1"
```

Topology Manager would consider this pod. The Topology Manager consults the CPU Manager static policy, which returns the topology of available CPUs. Topology Manager also consults Device Manager to discover the topology of available devices for example.com/device.

Topology Manager will use this information to store the best Topology for this container. In the case of this pod, CPU Manager and Device Manager will use this stored information at the resource allocation stage.

CHAPTER 9. SCALING THE CLUSTER MONITORING OPERATOR

OpenShift Container Platform exposes metrics that the Cluster Monitoring Operator collects and stores in the Prometheus-based monitoring stack. As an administrator, you can view system resources, containers and components metrics in one dashboard interface, Grafana.



IMPORTANT

If you are running cluster monitoring with an attached PVC for Prometheus, you might experience OOM kills during cluster upgrade. When persistent storage is in use for Prometheus, Prometheus memory usage doubles during cluster upgrade and for several hours after upgrade is complete. To avoid the OOM kill issue, allow worker nodes with double the size of memory that was available prior to the upgrade. For example, if you are running monitoring on the minimum recommended nodes, which is 2 cores with 8 GB of RAM, increase memory to 16 GB. For more information, see BZ#1925061.

9.1. PROMETHEUS DATABASE STORAGE REQUIREMENTS

Red Hat performed various tests for different scale sizes.



NOTE

The Prometheus storage requirements below are not prescriptive. Higher resource consumption might be observed in your cluster depending on workload activity and resource use.

Table 9.1. Prometheus Database storage requirements based on number of nodes/pods in the cluster

Number of Nodes	Number of pods	Prometheus storage growth per day	Prometheus storage growth per 15 days	RAM Space (per scale size)	Network (per tsdb chunk)
50	1800	6.3 GB	94 GB	6 GB	16 MB
100	3600	13 GB	195 GB	10 GB	26 MB
150	5400	19 GB	283 GB	12 GB	36 MB
200	7200	25 GB	375 GB	14 GB	46 MB

Approximately 20 percent of the expected size was added as overhead to ensure that the storage requirements do not exceed the calculated value.

The above calculation is for the default OpenShift Container Platform Cluster Monitoring Operator.



NOTE

CPU utilization has minor impact. The ratio is approximately 1 core out of 40 per 50 nodes and 1800 pods.

Recommendations for OpenShift Container Platform

- Use at least three infrastructure (infra) nodes.
- Use at least three **openshift-container-storage** nodes with non-volatile memory express (NVMe) drives.

9.2. CONFIGURING CLUSTER MONITORING

Procedure

To increase the storage capacity for Prometheus:

1. Create a YAML configuration file, **cluster-monitoring-config.yml**. For example:

```
apiVersion: v1
kind: ConfigMap
data:
 config.yaml: |
  prometheusOperator:
   baselmage: quay.io/coreos/prometheus-operator
   prometheusConfigReloaderBaseImage: quay.io/coreos/prometheus-config-reloader
   configReloaderBaseImage: quay.io/coreos/configmap-reload
   nodeSelector:
    node-role.kubernetes.io/infra: ""
  prometheusK8s:
   retention: {{PROMETHEUS_RETENTION_PERIOD}}
   baseImage: openshift/prometheus
   nodeSelector:
    node-role.kubernetes.io/infra: ""
   volumeClaimTemplate:
    spec:
     storageClassName: gp2
     resources:
      requests:
        storage: {{PROMETHEUS_STORAGE_SIZE}} 2
  alertmanagerMain:
   baseImage: openshift/prometheus-alertmanager
   nodeSelector:
    node-role.kubernetes.io/infra: ""
   volumeClaimTemplate:
    spec:
     storageClassName: gp2
     resources:
      requests:
        storage: {{ALERTMANAGER_STORAGE_SIZE}} 3
  nodeExporter:
   baseImage: openshift/prometheus-node-exporter
  kubeRbacProxy:
   baselmage: quay.io/coreos/kube-rbac-proxy
```

kubeStateMetrics:
 baseImage: quay.io/coreos/kube-state-metrics
 nodeSelector:
 node-role.kubernetes.io/infra: ""
 grafana:
 baseImage: grafana/grafana
 nodeSelector:
 node-role.kubernetes.io/infra: ""
 auth:
 baseImage: openshift/oauth-proxy
 k8sPrometheusAdapter:
 nodeSelector:
 node-role.kubernetes.io/infra: ""
 metadata:
 name: cluster-monitoring-config
 namespace: openshift-monitoring

- A typical value is **PROMETHEUS_RETENTION_PERIOD=15d**. Units are measured in time using one of these suffixes: s, m, h, d.
- A typical value is **PROMETHEUS_STORAGE_SIZE=2000Gi**. Storage values can be a plain integer or as a fixed-point integer using one of these suffixes: E, P, T, G, M, K. You can also use the power-of-two equivalents: Ei, Pi, Ti, Gi, Mi, Ki.
- A typical value is **ALERTMANAGER_STORAGE_SIZE=20Gi**. Storage values can be a plain integer or as a fixed-point integer using one of these suffixes: E, P, T, G, M, K. You can also use the power-of-two equivalents: Ei, Pi, Ti, Gi, Mi, Ki.
- 2. Set the values like the retention period and storage sizes.
- 3. Apply the changes by running:

\$ oc create -f cluster-monitoring-config.yml

CHAPTER 10. THE NODE FEATURE DISCOVERY OPERATOR

Learn about the Node Feature Discovery (NFD) Operator and how you can use it to expose node-level information by orchestrating Node Feature Discovery, a Kubernetes add-on for detecting hardware features and system configuration.

10.1. ABOUT THE NODE FEATURE DISCOVERY OPERATOR

The Node Feature Discovery Operator (NFD) manages the detection of hardware features and configuration in a OpenShift Container Platform cluster by labeling the nodes with hardware-specific information. NFD labels the host with node-specific attributes, such as PCI cards, kernel, operating system version, and so on.

The NFD Operator can be found on the Operator Hub by searching for "Node Feature Discovery".

10.2. INSTALLING THE NODE FEATURE DISCOVERY OPERATOR

The Node Feature Discovery (NFD) Operator orchestrates all resources needed to run the NFD daemon set. As a cluster administrator, you can install the NFD Operator using the OpenShift Container Platform CLI or the web console.

10.2.1. Installing the NFD Operator using the CLI

As a cluster administrator, you can install the NFD Operator using the CLI.

Prerequisites

- An OpenShift Container Platform cluster
- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.

Procedure

- 1. Create a namespace for the NFD Operator.
 - a. Create the following **Namespace** custom resource (CR) that defines the **openshift-nfd** namespace, and then save the YAML in the **nfd-namespace.yaml** file:

apiVersion: v1 kind: Namespace metadata:

name: openshift-nfd

- b. Create the namespace by running the following command:
 - \$ oc create -f nfd-namespace.yaml
- 2. Install the NFD Operator in the namespace you created in the previous step by creating the following objects:
 - a. Create the following **OperatorGroup** CR and save the YAML in the **nfd-operatorgroup.yaml** file:

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

generateName: openshift-nfd-

name: openshift-nfd namespace: openshift-nfd

spec:

targetNamespaces:
- openshift-nfd

b. Create the **OperatorGroup** CR by running the following command:

\$ oc create -f nfd-operatorgroup.yaml

c. Run the following command to get the **channel** value required for the next step.

\$ oc get packagemanifest nfd -n openshift-marketplace -o jsonpath='{.status.defaultChannel}'

Example output

4.8

d. Create the following Subscription CR and save the YAML in the nfd-sub.yaml file:

Example Subscription

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata: name: nfd

namespace: openshift-nfd

spec:

channel: "4.8"

installPlanApproval: Automatic

name: nfd

source: redhat-operators

sourceNamespace: openshift-marketplace

e. Create the subscription object by running the following command:

\$ oc create -f nfd-sub.yaml

f. Change to the **openshift-nfd** project:

\$ oc project openshift-nfd

Verification

• To verify that the Operator deployment is successful, run:

\$ oc get pods

Example output

NAME READY STATUS RESTARTS AGE nfd-controller-manager-7f86ccfb58-vgr4x 2/2 Running 0 10m

A successful deployment shows a **Running** status.

10.2.2. Installing the NFD Operator using the web console

As a cluster administrator, you can install the NFD Operator using the web console.



NOTE

It is recommended to create the **Namespace** as mentioned in the previous section.

Procedure

- 1. In the OpenShift Container Platform web console, click **Operators** → **OperatorHub**.
- 2. Choose **Node Feature Discovery** from the list of available Operators, and then click **Install**.
- 3. On the **Install Operator** page, select a **specific namespace on the cluster** select the namespace created in the previous section, and then click **Install**.

Verification

To verify that the NFD Operator installed successfully:

- 1. Navigate to the **Operators** → **Installed Operators** page.
- 2. Ensure that **Node Feature Discovery** is listed in the **openshift-nfd** project with a **Status** of **InstallSucceeded**.



NOTE

During installation an Operator might display a **Failed** status. If the installation later succeeds with an **InstallSucceeded** message, you can ignore the **Failed** message.

Troubleshooting

If the Operator does not appear as installed, troubleshoot further:

- Navigate to the Operators → Installed Operators page and inspect the Operator Subscriptions and Install Plans tabs for any failure or errors under Status.
- 2. Navigate to the **Workloads** → **Pods** page and check the logs for pods in the **openshift-nfd** project.

10.3. USING THE NODE FEATURE DISCOVERY OPERATOR

The Node Feature Discovery (NFD) Operator orchestrates all resources needed to run the Node-Feature-Discovery daemon set by watching for a **NodeFeatureDiscovery** CR. Based on the **NodeFeatureDiscovery** CR, the Operator will create the operand (NFD) components in the desired

namespace. You can edit the CR to choose another **namespace**, **image**, **imagePullPolicy**, and **nfd-worker-conf**, among other options.

As a cluster administrator, you can create a **NodeFeatureDiscovery** instance using the OpenShift Container Platform CLI or the web console.

10.3.1. Create a NodeFeatureDiscovery instance using the CLI

As a cluster administrator, you can create a **NodeFeatureDiscovery** CR instance using the CLI.

Prerequisites

- An OpenShift Container Platform cluster
- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.
- Install the NFD Operator.

Procedure

1. Create the following **NodeFeatureDiscovery** Custom Resource (CR), and then save the YAML in the **NodeFeatureDiscovery.yaml** file:

```
apiVersion: nfd.openshift.io/v1
kind: NodeFeatureDiscovery
metadata:
 name: nfd-instance
 namespace: openshift-nfd
 instance: "" # instance is empty by default
 operand:
  namespace: openshift-nfd
  image: quay.io/openshift/origin-node-feature-discovery:4.8
  imagePullPolicy: Always
 workerConfig:
  configData: |
   #core:
   # labelWhiteList:
   # noPublish: false
   # sleepInterval: 60s
   # sources: [all]
   # klog:
   # addDirHeader: false
   # alsologtostderr: false
   # logBacktraceAt:
   # logtostderr: true
   # skipHeaders: false
   # stderrthreshold: 2
   # v: 0
   # vmodule:
   ## NOTE: the following options are not dynamically run-time configurable
           and require a nfd-worker restart to take effect after being changed
   ##
      logDir:
```

```
# logFile:
# logFileMaxSize: 1800
# skipLogHeaders: false
#sources:
# cpu:
# cpuid:
   NOTE: whitelist has priority over blacklist
    attributeBlacklist:
  - "BMI1"
    - "BMI2"
#
#
  - "CLMUL"
  - "CMOV"
#
    - "CX16"
  - "ERMS"
    - "F16C"
   - "HTT"
   - "LZCNT"
    - "MMX"
    - "MMXEXT"
    - "NX"
    - "POPCNT"
    - "RDRAND"
    - "RDSEED"
    - "RDTSCP"
    - "SGX"
#
    - "SSE"
#
   - "SSE2"
    - "SSE3"
  - "SSE4.1"
#
    - "SSE4.2"
     - "SSSE3"
#
    attributeWhitelist:
# kernel:
# kconfigFile: "/path/to/kconfig"
# configOpts:
# - "NO_HZ"
  - "X86"
#
   - "DMI"
# pci:
# deviceClassWhitelist:
  - "0200"
# - "03"
# - "12"
# deviceLabelFields:
  - "class"
  - "vendor"
  - "device"
    - "subsystem_vendor"
#
    - "subsystem_device"
# usb:
# deviceClassWhitelist:
# - "0e"
# - "ef"
# - "fe"
  - "ff"
   deviceLabelFields:
```

```
- "class"
      - "vendor"
      - "device"
  # custom:
  # - name: "my.kernel.feature"
     matchOn:
       - loadedKMod: ["example_kmod1", "example_kmod2"]
    - name: "my.pci.feature"
      matchOn:
       - pcild:
  #
  #
          class: ["0200"]
          vendor: ["15b3"]
          device: ["1014", "1017"]
  #
      - pcild :
  #
         vendor: ["8086"]
          device: ["1000", "1100"]
  # - name: "my.usb.feature"
      matchOn:
      - usbld:
        class: ["ff"]
  #
       vendor: ["03e7"]
       device: ["2485"]
  #
      usbld:
       class: ["fe"]
       vendor: ["1a6e"]
  #
        device: ["089a"]
  # - name: "my.combined.feature"
      matchOn:
      - pcild:
  #
          vendor: ["15b3"]
          device: ["1014", "1017"]
         loadedKMod : ["vendor_kmod1", "vendor_kmod2"]
customConfig:
 configData: |
  # - name: "more.kernel.features"
      matchOn:
     - loadedKMod: ["example kmod3"]
  # - name: "more.features.by.nodename"
     value: customValue
      matchOn:
      - nodename: ["special-.*-node-.*"]
```

2. Create the **NodeFeatureDiscovery** CR instance by running the following command:

\$ oc create -f NodeFeatureDiscovery.yaml

Verification

• To verify that the instance is created, run:

\$ oc get pods

Example output

NAME	READY	STATUS RE	STARTS	AGE
nfd-controller-manager-7f86c	cfb58-vgr	4x 2/2 Runni	ing 0	11m
nfd-master-hcn64	1/1	Running 0	60s	
nfd-master-Innxx	1/1	Running 0	60s	
nfd-master-mp6hr	1/1	Running 0	60s	
nfd-worker-vgcz9	1/1	Running 0	60s	
nfd-worker-xqbws	1/1	Running 0	60s	

A successful deployment shows a **Running** status.

10.3.2. Create a NodeFeatureDiscovery CR using the web console

Procedure

- 1. Navigate to the **Operators** → **Installed Operators** page.
- 2. Find Node Feature Discovery and see a box under Provided APIs.
- 3. Click Create instance.
- 4. Edit the values of the **NodeFeatureDiscovery** CR.
- 5. Click Create.

10.4. CONFIGURING THE NODE FEATURE DISCOVERY OPERATOR

10.4.1. core

The core section contains common configuration settings that are not specific to any particular feature source.

core.sleepInterval

core.sleepInterval specifies the interval between consecutive passes of feature detection or redetection, and thus also the interval between node re-labeling. A non-positive value implies infinite sleep interval; no re-detection or re-labeling is done.

This value is overridden by the deprecated **--sleep-interval** command line flag, if specified.

Example usage

sleepInterval: 60s 1



The default value is 60s.

core.sources

core.sources specifies the list of enabled feature sources. A special value all enables all feature sources.

This value is overridden by the deprecated **--sources** command line flag, if specified.

Default: [all]

Example usage

core:

sources:

- system
- custom

core.labelWhiteList

core.labelWhiteList specifies a regular expression for filtering feature labels based on the label name. Non-matching labels are not published.

The regular expression is only matched against the basename part of the label, the part of the name after '/'. The label prefix, or namespace, is omitted.

This value is overridden by the deprecated **--label-whitelist** command line flag, if specified.

Default: **null**

Example usage

core:

labelWhiteList: '^cpu-cpuid'

core.noPublish

Setting **core.noPublish** to **true** disables all communication with the **nfd-master**. It is effectively a dry run flag; **nfd-worker** runs feature detection normally, but no labeling requests are sent to **nfd-master**.

This value is overridden by the --no-publish command line flag, if specified.

Example:

Example usage

core:

noPublish: true 1

The default value is false.

core.klog

The following options specify the logger configuration, most of which can be dynamically adjusted at run-time.

The logger options can also be specified using command line flags, which take precedence over any corresponding config file options.

core.klog.addDirHeader

If set to true, core.klog.addDirHeader adds the file directory to the header of the log messages.

Default: false

Run-time configurable: yes

core.klog.alsologtostderr

Log to standard error as well as files.

Default: false

Run-time configurable: yes

core.klog.logBacktraceAt

When logging hits line file:N, emit a stack trace.

Default: empty

Run-time configurable: yes

core.klog.logDir

If non-empty, write log files in this directory.

Default: empty

Run-time configurable: no

core.klog.logFile

If not empty, use this log file.

Default: empty

Run-time configurable: no

core.klog.logFileMaxSize

core.klog.logFileMaxSize defines the maximum size a log file can grow to. Unit is megabytes. If the value is **0**, the maximum file size is unlimited.

Default: 1800

Run-time configurable: no

core.klog.logtostderr

Log to standard error instead of files

Default: true

Run-time configurable: yes

core.klog.skipHeaders

If core.klog.skipHeaders is set to true, avoid header prefixes in the log messages.

Default: false

Run-time configurable: yes

core.klog.skipLogHeaders

If core.klog.skipLogHeaders is set to true, avoid headers when opening log files.

Default: false

Run-time configurable: no

core.klog.stderrthreshold

Logs at or above this threshold go to stderr.

Default: 2

Run-time configurable: yes

core.klog.v

core.klog.v is the number for the log level verbosity.

Default: 0

Run-time configurable: yes

core.klog.vmodule

core.klog.vmodule is a comma-separated list of pattern=N settings for file-filtered logging.

Default: empty

Run-time configurable: yes

10.4.2. sources

The **sources** section contains feature source specific configuration parameters.

sources.cpu.cpuid.attributeBlacklist

Prevent publishing **cpuid** features listed in this option.

This value is overridden by **sources.cpu.cpuid.attributeWhitelist**, if specified.

Default: [BMI1, BMI2, CLMUL, CMOV, CX16, ERMS, F16C, HTT, LZCNT, MMX, MMXEXT, NX, POPCNT, RDRAND, RDSEED, RDTSCP, SGX, SGXLC, SSE, SSE2, SSE3, SSE4.1, SSE4.2, SSSE3]

Example usage

```
sources:
cpu:
cpuid:
attributeBlacklist: [MMX, MMXEXT]
```

sources.cpu.cpuid.attributeWhitelist

Only publish the **cpuid** features listed in this option.

sources.cpu.cpuid.attributeWhitelist takes precedence over sources.cpu.cpuid.attributeBlacklist.

Default: empty

Example usage

```
sources:
cpu:
cpuid:
attributeWhitelist: [AVX512BW, AVX512CD, AVX512DQ, AVX512F, AVX512VL]
```

sources.kernel.kconfigFile

sources.kernel.kconfigFile is the path of the kernel config file. If empty, NFD runs a search in the well-known standard locations.

Default: empty

Example usage

sources: kernel:

kconfigFile: "/path/to/kconfig"

sources.kernel.configOpts

sources.kernel.configOpts represents kernel configuration options to publish as feature labels.

Default: [NO_HZ, NO_HZ_IDLE, NO_HZ_FULL, PREEMPT]

Example usage

sources: kernel:

configOpts: [NO_HZ, X86, DMI]

soures.pci.deviceClassWhitelist

soures.pci.deviceClassWhitelist is a list of PCI device class IDs for which to publish a label. It can be specified as a main class only (for example, **03**) or full class-subclass combination (for example **0300**). The former implies that all subclasses are accepted. The format of the labels can be further configured with **deviceLabelFields**.

Default: ["03", "0b40", "12"]

Example usage

sources:

pci:

deviceClassWhitelist: ["0200", "03"]

soures.pci.deviceLabelFields

soures.pci.deviceLabelFields is the set of PCI ID fields to use when constructing the name of the feature label. Valid fields are **class**, **vendor**, **device**, **subsystem_vendor** and **subsystem_device**.

Default: [class, vendor]

Example usage

sources:

pci:

deviceLabelFields: [class, vendor, device]

With the example config above, NFD would publish labels such as **feature.node.kubernetes.io/pci-class-id>_cvendor-id>_cdevice-id>.present=true**

soures.usb.deviceClassWhitelist

soures.usb.deviceClassWhitelist is a list of USB device class IDs for which to publish a feature label. The format of the labels can be further configured with **deviceLabelFields**.

Default: ["0e", "ef", "fe", "ff"]

Example usage

sources:
usb:
deviceClassWhitelist: ["ef", "ff"]

soures.usb.deviceLabelFields

soures.usb.deviceLabelFields is the set of USB ID fields from which to compose the name of the feature label. Valid fields are **class**, **vendor**, and **device**.

Default: [class, vendor, device]

Example usage

sources:
pci:
deviceLabelFields: [class, vendor]

With the example config above, NFD would publish labels like: **feature.node.kubernetes.io/usb-<class-id>_<vendor-id>.present=true**.

soures.custom

soures.custom is the list of rules to process in the custom feature source to create user-specific labels.

Default: empty

Example usage

source:

custom:

name: "my.custom.feature" matchOn:

- loadedKMod: ["e1000e"]

- pcild:

class: ["0200"] vendor: ["8086"]

CHAPTER 11. THE DRIVER TOOLKIT

Learn about the Driver Toolkit and how you can use it as a base image for driver containers for enabling special software and hardware devices on Kubernetes.



IMPORTANT

The Driver Toolkit is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see https://access.redhat.com/support/offerings/techpreview/.

11.1. ABOUT THE DRIVER TOOLKIT

Background

The Driver Toolkit is a container image in the OpenShift Container Platform payload used as a base image on which you can build driver containers. The Driver Toolkit image contains the kernel packages commonly required as dependencies to build or install kernel modules, as well as a few tools needed in driver containers. The version of these packages will match the kernel version running on the Red Hat Enterprise Linux CoreOS (RHCOS) nodes in the corresponding OpenShift Container Platform release.

Driver containers are container images used for building and deploying out-of-tree kernel modules and drivers on container operating systems like RHCOS. Kernel modules and drivers are software libraries running with a high level of privilege in the operating system kernel. They extend the kernel functionalities or provide the hardware-specific code required to control new devices. Examples include hardware devices like Field Programmable Gate Arrays (FPGA) or GPUs, and software-defined storage (SDS) solutions, such as Lustre parallel file systems, which require kernel modules on client machines. Driver containers are the first layer of the software stack used to enable these technologies on Kubernetes.

The list of kernel packages in the Driver Toolkit includes the following and their dependencies:

- kernel-core
- kernel-devel
- kernel-headers
- kernel-modules
- kernel-modules-extra

In addition, the Driver Toolkit also includes the corresponding real-time kernel packages:

- kernel-rt-core
- kernel-rt-devel
- kernel-rt-modules
- kernel-rt-modules-extra

The Driver Toolkit also has several tools which are commonly needed to build and install kernel modules, including:

- elfutils-libelf-devel
- kmod
- binutilskabi-dw
- kernel-abi-whitelists
- dependencies for the above

Purpose

Prior to the Driver Toolkit's existence, you could install kernel packages in a pod or build config on OpenShift Container Platform using entitled builds or by installing from the kernel RPMs in the hosts **machine-os-content**. The Driver Toolkit simplifies the process by removing the entitlement step, and avoids the privileged operation of accessing the machine-os-content in a pod. The Driver Toolkit can also be used by partners who have access to pre-released OpenShift Container Platform versions to prebuild driver-containers for their hardware devices for future OpenShift Container Platform releases.

The Driver Toolkit is also used by the Special Resource Operator (SRO), which is currently available as a community Operator on OperatorHub. SRO supports out-of-tree and third-party kernel drivers and the support software for the underlying operating system. Users can create *recipes* for SRO to build and deploy a driver container, as well as support software like a device plug-in, or metrics. Recipes can include a build config to build a driver container based on the Driver Toolkit, or SRO can deploy a prebuilt driver container.

11.2. PULLING THE DRIVER TOOLKIT CONTAINER IMAGE

The **driver-toolkit** image is available from the Container images section of the Red Hat Ecosystem Catalog and in the OpenShift Container Platform release payload. The image corresponding to the most recent minor release of OpenShift Container Platform will be tagged with the version number in the catalog. The image URL for a specific release can be found using the **oc adm** CLI command.

11.2.1. Pulling the Driver Toolkit container image from registry.redhat.io

Instructions for pulling the **driver-toolkit** image from **registry.redhat.io** with podman or in OpenShift Container Platform can be found on the Red Hat Ecosystem Catalog. The driver-toolkit image for the latest minor release will be tagged with the minor release version on registry.redhat.io for example **registry.redhat.io/openshift4/driver-toolkit-rhel8:v4.8**.

11.2.2. Finding the Driver Toolkit image URL in the payload

Prerequisites

- Obtain the image pull secret needed to perform an installation of OpenShift Container Platform, from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.
- Install the OpenShift CLI (oc).

Procedure

1. The image URL of the **driver-toolkit** corresponding to a certain release can be extracted from the release image using the **oc adm** command:

\$ oc adm release info 4.8.0 --image-for=driver-toolkit

Example output

quay.io/openshift-release-dev/ocp-v4.0-art-dev@sha256:0fd84aee79606178b6561ac71f8540f404d518ae5deff45f6d6ac8f02636c7f4

2. This image can be pulled using a valid pull secret, such as the pull secret required to install OpenShift Container Platform.

\$ podman pull --authfile=path/to/pullsecret.json quay.io/openshift-release-dev/ocp-v4.0-art-dev@sha256:<SHA>

11.3. USING THE DRIVER TOOLKIT

As an example, the Driver Toolkit can be used as the base image for building a very simple kernel module called simple-kmod.

11.3.1. Build and run the simple-kmod driver container on a cluster

Prerequisites

- An OpenShift Container Platform cluster
- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.

Procedure

Create a namespace. For example:

\$ oc new-project simple-kmod-demo

 The YAML defines an ImageStream for storing the simple-kmod driver container image, and a BuildConfig for building the container. Save this YAML as 0000-buildconfig.yaml.template.

apiVersion: image.openshift.io/v1
kind: ImageStream
metadata:
labels:
 app: simple-kmod-driver-container
 name: simple-kmod-driver-container
 namespace: simple-kmod-demo
spec: {}
--apiVersion: build.openshift.io/v1
kind: BuildConfig
metadata:
labels:
 app: simple-kmod-driver-build
name: simple-kmod-driver-build
namespace: simple-kmod-demo

```
spec:
 nodeSelector:
  node-role.kubernetes.io/worker: ""
 runPolicy: "Serial"
 triggers:
  - type: "ConfigChange"
  - type: "ImageChange"
 source:
  ait:
   ref: "master"
   uri: "https://github.com/openshift-psap/kvc-simple-kmod.git"
  type: Git
  dockerfile: |
   FROM DRIVER_TOOLKIT_IMAGE
   WORKDIR /build/
   RUN yum -y install git make sudo gcc \
   && yum clean all \
   && rm -rf /var/cache/dnf
   # Expecting kmod software version as an input to the build
   ARG KMODVER
   # Grab the software from upstream
   RUN git clone https://github.com/openshift-psap/simple-kmod.git
   WORKDIR simple-kmod
   # Prep and build the module
   RUN make buildprep KVER=$(rpm -q --qf "%{VERSION}-%{RELEASE}.%{ARCH}"
kernel-core) KMODVER=${KMODVER} \
                  KVER=$(rpm -q --qf "%{VERSION}-%{RELEASE}.%{ARCH}" kernel-
   && make all
core) KMODVER=${KMODVER} \
   && make install KVER=$(rpm -q --qf "%{VERSION}-%{RELEASE}.%{ARCH}" kernel-
core) KMODVER=${KMODVER}
   # Add the helper tools
   WORKDIR /root/kvc-simple-kmod
   ADD Makefile.
   ADD simple-kmod-lib.sh.
   ADD simple-kmod-wrapper.sh.
   ADD simple-kmod.conf.
   RUN mkdir -p /usr/lib/kvc/ \
   && mkdir -p /etc/kvc/ \
   && make install
   RUN systemctl enable kmods-via-containers@simple-kmod
 strategy:
  dockerStrategy:
   buildArgs:
    - name: KMODVER
     value: DEMO
 output:
  to:
   kind: ImageStreamTag
   name: simple-kmod-driver-container:demo
```

2. Substitute the correct driver toolkit image for the OpenShift Container Platform version you are running in place of "DRIVER_TOOLKIT_IMAGE" with the following commands.

\$ OCP_VERSION=\$(oc get clusterversion/version -ojsonpath={.status.desired.version})

\$ DRIVER_TOOLKIT_IMAGE=\$(oc adm release info \$OCP_VERSION --image-for=driver-toolkit)

\$ sed "s#DRIVER_TOOLKIT_IMAGE#\${DRIVER_TOOLKIT_IMAGE}#" 0000-buildconfig.yaml.template > 0000-buildconfig.yaml



NOTE

The driver toolkit was introduced to OpenShift Container Platform 4.6 as of version 4.6.30, in 4.7 as of version 4.7.11, and in 4.8.

3. Create the image stream and build config with

\$ oc create -f 0000-buildconfig.yaml

- 4. After the builder pod completes successfully, deploy the driver container image as a **DaemonSet**.
 - a. The driver container must run with the privileged security context in order to load the kernel modules on the host. The following YAML file contains the RBAC rules and the **DaemonSet** for running the driver container. Save this YAML as **1000-drivercontainer.yaml**.

apiVersion: v1

kind: ServiceAccount

metadata:

name: simple-kmod-driver-container

apiVersion: rbac.authorization.k8s.io/v1

kind: Role metadata:

name: simple-kmod-driver-container

rules:

- apiGroups:
 - security.openshift.io

resources:

- securitycontextconstraints

verbs:

- use

resourceNames:

- privileged

apiVersion: rbac.authorization.k8s.io/v1

kind: RoleBinding

metadata:

name: simple-kmod-driver-container

roleRef:

apiGroup: rbac.authorization.k8s.io

kind: Role

```
name: simple-kmod-driver-container
subjects:
- kind: ServiceAccount
 name: simple-kmod-driver-container
userNames:
- system:serviceaccount:simple-kmod-demo:simple-kmod-driver-container
apiVersion: apps/v1
kind: DaemonSet
metadata:
 name: simple-kmod-driver-container
spec:
 selector:
  matchLabels:
   app: simple-kmod-driver-container
 template:
  metadata:
   labels:
    app: simple-kmod-driver-container
  spec:
   serviceAccount: simple-kmod-driver-container
   serviceAccountName: simple-kmod-driver-container
   containers:
   - image: image-registry.openshift-image-registry.svc:5000/simple-kmod-
demo/simple-kmod-driver-container:demo
    name: simple-kmod-driver-container
    imagePullPolicy: Always
    command: ["/sbin/init"]
    lifecycle:
      preStop:
       exec:
        command: ["/bin/sh", "-c", "systemctl stop kmods-via-containers@simple-kmod"]
    securityContext:
      privileged: true
   nodeSelector:
    node-role.kubernetes.io/worker: ""
```

b. Create the RBAC rules and daemon set:

\$ oc create -f 1000-drivercontainer.yaml

- 5. After the pods are running on the worker nodes, verify that the **simple_kmod** kernel module is loaded successfully on the host machines with **Ismod**.
 - a. Verify that the pods are running:

\$ oc get pod -n simple-kmod-demo

Example output

NAME	READY	STA	TUS RE	STAF	RTS AGE
simple-kmod-driver-build-	I-build	0/1	Completed	0	6m
simple-kmod-driver-contai	ner-b22fd	d 1/1	Running	0	40s
simple-kmod-driver-contai	ner-jz9vr	1/1	Running	0	40s
simple-kmod-driver-contai	ner-p45c	c 1/1	Running	0	40s

b. Execute the **Ismod** command in the driver container pod:

\$ oc exec -it pod/simple-kmod-driver-container-p45cc -- Ismod | grep simple

Example output

simple_procfs_kmod 16384 0 simple_kmod 16384 0

CHAPTER 12. PLANNING YOUR ENVIRONMENT ACCORDING TO OBJECT MAXIMUMS

Consider the following tested object maximums when you plan your OpenShift Container Platform cluster.

These guidelines are based on the largest possible cluster. For smaller clusters, the maximums are lower. There are many factors that influence the stated thresholds, including the etcd version or storage data format.



IMPORTANT

These guidelines apply to OpenShift Container Platform with software-defined networking (SDN), not Open Virtual Network (OVN).

In most cases, exceeding these numbers results in lower overall performance. It does not necessarily mean that the cluster will fail.

12.1. OPENSHIFT CONTAINER PLATFORM TESTED CLUSTER MAXIMUMS FOR MAJOR RELEASES

Tested Cloud Platforms for OpenShift Container Platform 3.x: Red Hat OpenStack Platform (RHOSP), Amazon Web Services and Microsoft Azure. Tested Cloud Platforms for OpenShift Container Platform 4.x: Amazon Web Services, Microsoft Azure and Google Cloud Platform.

Maximum type	3.x tested maximum	4.x tested maximum
Number of nodes	2,000	2,000
Number of pods ^[1]	150,000	150,000
Number of pods per node	250	500 [2]
Number of pods per core	There is no default value.	There is no default value.
Number of namespaces ^[3]	10,000	10,000
Number of builds	10,000 (Default pod RAM 512 Mi) - Pipeline Strategy	10,000 (Default pod RAM 512 Mi) - Source-to-Image (S2I) build strategy
Number of pods per namespace [4]	25,000	25,000
Number of services ^[5]	10,000	10,000
Number of services per namespace	5,000	5,000

Maximum type	3.x tested maximum	4.x tested maximum
Number of back-ends per service	5,000	5,000
Number of deployments per namespace ^[4]	2,000	2,000

- 1. The pod count displayed here is the number of test pods. The actual number of pods depends on the application's memory, CPU, and storage requirements.
- 2. This was tested on a cluster with 100 worker nodes with 500 pods per worker node. The default maxPods is still 250. To get to 500 maxPods, the cluster must be created with a maxPods set to 500 using a custom kubelet config. If you need 500 user pods, you need a hostPrefix of 22 because there are 10-15 system pods already running on the node. The maximum number of pods with attached persistent volume claims (PVC) depends on storage backend from where PVC are allocated. In our tests, only OpenShift Container Storage v4 (OCS v4) was able to satisfy the number of pods per node discussed in this document.
- 3. When there are a large number of active projects, etcd might suffer from poor performance if the keyspace grows excessively large and exceeds the space quota. Periodic maintenance of etcd, including defragmentaion, is highly recommended to free etcd storage.
- 4. There are a number of control loops in the system that must iterate over all objects in a given namespace as a reaction to some changes in state. Having a large number of objects of a given type in a single namespace can make those loops expensive and slow down processing given state changes. The limit assumes that the system has enough CPU, memory, and disk to satisfy the application requirements.
- 5. Each service port and each service back-end has a corresponding entry in iptables. The number of back-ends of a given service impact the size of the endpoints objects, which impacts the size of data that is being sent all over the system.

12.2. OPENSHIFT CONTAINER PLATFORM TESTED CLUSTER MAXIMUMS

The values in the following table were tested independently of each other and represent the maximum for that particular resource type. It might not be valid to consider these maximums in combinations. Appropriate capacity planning and testing should be performed for large environments. Other objects are created during the test runs, but are not close to the tested maximums. For example, when testing namespaces per cluster, deployments per namespace, or number of nodes, thousands of pods, services, deployments, secrets, config maps, and builds are created, but are not close to the cluster maximums.

Maximum type	4.1 and 4.2 tested maximum	4.3 tested maximum	4.4 tested maximum	4.5, 4.6, 4.7, and 4.8 tested maximum
Number of nodes	2,000	2,000	250	500
Number of pods ^[1]	150,000	150,000	62,500	62,500

Maximum type	4.1 and 4.2 tested maximum	4.3 tested maximum	4.4 tested maximum	4.5, 4.6, 4.7, and 4.8 tested maximum
Number of pods per node	250	500	500	500
Number of pods per core	There is no default value.	There is no default value.	There is no default value.	There is no default value.
Number of namespaces ^[2]	10,000	10,000	10,000	10,000
Number of builds	10,000 (Default pod RAM 512 Mi) - Pipeline Strategy	10,000 (Default pod RAM 512 Mi) - Source-to-Image (S2I) build strategy	10,000 (Default pod RAM 512 Mi) - Source-to-Image (S2I) build strategy	10,000 (Default pod RAM 512 Mi) - Source-to-Image (S2I) build strategy
Number of pods per namespace ^[3]	25,000	25,000	25,000	25,000
Number of services ^[4]	10,000	10,000	10,000	10,000
Number of services per namespace	5,000	5,000	5,000	5,000
Number of back ends per service	5,000	5,000	5,000	5,000
Number of deployments per namespace [3]	2,000	2,000	2,000	2,000

- 1. The pod count displayed here is the number of test pods. The actual number of pods depends on the application's memory, CPU, and storage requirements.
- 2. When there are a large number of active projects, etcd might suffer from poor performance if the keyspace grows excessively large and exceeds the space quota. Periodic maintenance of etcd, including defragmentaion, is highly recommended to free etcd storage.
- 3. There are a number of control loops in the system that must iterate over all objects in a given namespace as a reaction to some changes in state. Having a large number of objects of a given type in a single namespace can make those loops expensive and slow down processing given state changes. The limit assumes that the system has enough CPU, memory, and disk to satisfy the application requirements.

4. Each service port and each service back end has a corresponding entry in iptables. The number of back ends of a given service impact the size of the endpoints objects, which impacts the size of data that is being sent all over the system.

In OpenShift Container Platform 4.8, half of a CPU core (500 millicore) is reserved by the system compared to OpenShift Container Platform 3.11 and previous versions.

12.3. OPENSHIFT CONTAINER PLATFORM ENVIRONMENT AND CONFIGURATION ON WHICH THE CLUSTER MAXIMUMS ARE TESTED

AWS cloud platform:

Node	Flavor	vCPU	RAM(GiB)	Disk type	Disk size(GiB) /IOS	Count	Region
Master/et	r5.4xlarge	16	128	io1	220 / 3000	3	us-west-2
Infra ^[2]	m5.12xlarg e	48	192	gp2	100	3	us-west-2
Workload [3]	m5.4xlarg e	16	64	gp2	500 [4]	1	us-west-2
Worker	m5.2xlarg e	8	32	gp2	100	3/25/250 /500 ^[5]	us-west-2

- 1. io1 disks with 3000 IOPS are used for master/etcd nodes as etcd is I/O intensive and latency sensitive.
- 2. Infra nodes are used to host Monitoring, Ingress, and Registry components to ensure they have enough resources to run at large scale.
- 3. Workload node is dedicated to run performance and scalability workload generators.
- 4. Larger disk size is used so that there is enough space to store the large amounts of data that is collected during the performance and scalability test run.
- 5. Cluster is scaled in iterations and performance and scalability tests are executed at the specified node counts.

IBM Power Systems platform:

Node	vCPU	RAM(GiB)	Disk type	Disk size(GiB)/IOS	Count
Master/etcd ^[1]	16	32	io1	120 / 3 IOPS per GB	3

Node	vCPU	RAM(GiB)	Disk type	Disk size(GiB)/IOS	Count
Infra ^[2]	16	64	gp2	120	2
Workload ^[3]	16	256	gp2	120 [4]	1
Worker	16	64	gp2	120	3/25/250/50 0 ^[5]

- 1. io1 disks with 120 / 3 IOPS per GB are used for master/etcd nodes as etcd is I/O intensive and latency sensitive.
- 2. Infra nodes are used to host Monitoring, Ingress, and Registry components to ensure they have enough resources to run at large scale.
- 3. Workload node is dedicated to run performance and scalability workload generators.
- 4. Larger disk size is used so that there is enough space to store the large amounts of data that is collected during the performance and scalability test run.
- 5. Cluster is scaled in iterations and performance and scalability tests are executed at the specified node counts.

12.4. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO TESTED CLUSTER MAXIMUMS



IMPORTANT

Oversubscribing the physical resources on a node affects resource guarantees the Kubernetes scheduler makes during pod placement. Learn what measures you can take to avoid memory swapping.

Some of the tested maximums are stretched only in a single dimension. They will vary when many objects are running on the cluster.

The numbers noted in this documentation are based on Red Hat's test methodology, setup, configuration, and tunings. These numbers can vary based on your own individual setup and environments.

While planning your environment, determine how many pods are expected to fit per node:

required pods per cluster / pods per node = total number of nodes needed

The current maximum number of pods per node is 250. However, the number of pods that fit on a node is dependent on the application itself. Consider the application's memory, CPU, and storage requirements, as described in *How to plan your environment according to application requirements*.

Example scenario

If you want to scope your cluster for 2200 pods per cluster, you would need at least five nodes, assuming that there are 500 maximum pods per node:

2200 / 500 = 4.4

If you increase the number of nodes to 20, then the pod distribution changes to 110 pods per node:

2200 / 20 = 110

Where:

required pods per cluster / total number of nodes = expected pods per node

12.5. HOW TO PLAN YOUR ENVIRONMENT ACCORDING TO APPLICATION REQUIREMENTS

Consider an example application environment:

Pod type	Pod quantity	Max memory	CPU cores	Persistent storage
apache	100	500 MB	0.5	1GB
node.js	200	1GB	1	1GB
postgresql	100	1GB	2	10 GB
JBoss EAP	100	1GB	1	1GB

Extrapolated requirements: 550 CPU cores, 450GB RAM, and 1.4TB storage.

Instance size for nodes can be modulated up or down, depending on your preference. Nodes are often resource overcommitted. In this deployment scenario, you can choose to run additional smaller nodes or fewer larger nodes to provide the same amount of resources. Factors such as operational agility and cost-per-instance should be considered.

Node type	Quantity	CPUs	RAM (GB)
Nodes (option 1)	100	4	16
Nodes (option 2)	50	8	32
Nodes (option 3)	25	16	64

Some applications lend themselves well to overcommitted environments, and some do not. Most Java applications and applications that use huge pages are examples of applications that would not allow for overcommitment. That memory can not be used for other applications. In the example above, the environment would be roughly 30 percent overcommitted, a common ratio.

The application pods can access a service either by using environment variables or DNS. If using environment variables, for each active service the variables are injected by the kubelet when a pod is run on a node. A cluster-aware DNS server watches the Kubernetes API for new services and creates a set of DNS records for each one. If DNS is enabled throughout your cluster, then all pods should automatically be able to resolve services by their DNS name. Service discovery using DNS can be used in case you must go beyond 5000 services. When using environment variables for service discovery, the argument list exceeds the allowed length after 5000 services in a namespace, then the pods and deployments will start failing. Disable the service links in the deployment's service specification file to overcome this:

```
Kind: Template
  apiVersion: v1
  metadata:
   name: deploymentConfigTemplate
   creationTimestamp:
   annotations:
    description: This template will create a deploymentConfig with 1 replica, 4 env vars and a
service.
    tags: "
  objects:
  - kind: DeploymentConfig
   apiVersion: v1
   metadata:
    name: deploymentconfig${IDENTIFIER}
   spec:
    template:
      metadata:
       labels:
        name: replicationcontroller${IDENTIFIER}
      spec:
       enableServiceLinks: false
       containers:
       - name: pause${IDENTIFIER}
        image: "${IMAGE}"
        ports:
        - containerPort: 8080
         protocol: TCP
        env:
        - name: ENVVAR1 ${IDENTIFIER}
         value: "${ENV VALUE}"
        - name: ENVVAR2 ${IDENTIFIER}
         value: "${ENV_VALUE}"
        - name: ENVVAR3 ${IDENTIFIER}
         value: "${ENV VALUE}"
        - name: ENVVAR4 ${IDENTIFIER}
         value: "${ENV_VALUE}"
        resources: {}
        imagePullPolicy: IfNotPresent
        capabilities: {}
        securityContext:
         capabilities: {}
         privileged: false
       restartPolicy: Always
       serviceAccount: "
    replicas: 1
```

```
selector:
   name: replicationcontroller${IDENTIFIER}
  triggers:
  - type: ConfigChange
  strategy:
   type: Rolling
- kind: Service
 apiVersion: v1
 metadata:
  name: service${IDENTIFIER}
 spec:
  selector:
   name: replicationcontroller${IDENTIFIER}
  - name: serviceport${IDENTIFIER}
   protocol: TCP
   port: 80
   targetPort: 8080
  portallP: "
  type: ClusterIP
  sessionAffinity: None
 status:
  loadBalancer: {}
parameters:
- name: IDENTIFIER
 description: Number to append to the name of resources
 value: '1'
 required: true
- name: IMAGE
 description: Image to use for deploymentConfig
 value: gcr.io/google-containers/pause-amd64:3.0
 required: false
- name: ENV VALUE
 description: Value to use for environment variables
 generate: expression
 from: "[A-Za-z0-9]{255}"
 required: false
labels:
 template: deploymentConfigTemplate
```

The number of application pods that can run in a namespace is dependent on the number of services and the length of the service name when the environment variables are used for service discovery. **ARG_MAX** on the system defines the maximum argument length for a new process and it is set to **2097152 KiB** by default. The Kubelet injects environment variables in to each pod scheduled to run in the namespace including:

- <SERVICE_NAME>_SERVICE_HOST=<IP>
- <SERVICE_NAME>_SERVICE_PORT=<PORT>
- <SERVICE NAME> PORT=tcp://<IP>:<PORT>
- <SERVICE_NAME>_PORT_<PORT>_TCP=tcp://<IP>:<PORT>
- <SERVICE_NAME>_PORT_<PORT>_TCP_PROTO=tcp

- <SERVICE_NAME>_PORT_<PORT>_TCP_PORT=<PORT>
- <SERVICE_NAME>_PORT_<PORT>_TCP_ADDR=<ADDR>

The pods in the namespace will start to fail if the argument length exceeds the allowed value and the number of characters in a service name impacts it. For example, in a namespace with 5000 services, the limit on the service name is 33 characters, which enables you to run 5000 pods in the namespace.

CHAPTER 13. OPTIMIZING STORAGE

Optimizing storage helps to minimize storage use across all resources. By optimizing storage, administrators help ensure that existing storage resources are working in an efficient manner.

13.1. AVAILABLE PERSISTENT STORAGE OPTIONS

Understand your persistent storage options so that you can optimize your OpenShift Container Platform environment.

Table 13.1. Available storage options

Storage type	Description	Examples
Block	 Presented to the operating system (OS) as a block device Suitable for applications that need full control of storage and operate at a low level on files bypassing the file system Also referred to as a Storage Area Network (SAN) Non-shareable, which means that only one client at a time can mount an endpoint of this type 	AWS EBS and VMware vSphere support dynamic persistent volume (PV) provisioning natively in OpenShift Container Platform.
File	 Presented to the OS as a file system export to be mounted Also referred to as Network Attached Storage (NAS) Concurrency, latency, file locking mechanisms, and other capabilities vary widely between protocols, implementations, vendors, and scales. 	RHEL NFS, NetApp NFS ^[1] , and Vendor NFS
Object	 Accessible through a REST API endpoint Configurable for use in the OpenShift Container Platform Registry Applications must build their drivers into the application and/or container. 	AWS S3

1. NetApp NFS supports dynamic PV provisioning when using the Trident plug-in.



IMPORTANT

Currently, CNS is not supported in OpenShift Container Platform 4.8.

13.2. RECOMMENDED CONFIGURABLE STORAGE TECHNOLOGY

The following table summarizes the recommended and configurable storage technologies for the given OpenShift Container Platform cluster application.

Table 13.2. Recommended and configurable storage technology

Storage type	ROX1	RWX2	Registry	Scaled registry	Metrics3	Logging	Apps
Block	Yes ⁴	No	Configura ble	Not configura ble	Recomme nded	Recomme nded	Recomme nded
File	Yes ⁴	Yes	Configura ble	Configura ble	Configura ble ⁵	Configura ble ⁶	Recomme nded
Object	Yes	Yes	Recomme nded	Recomme nded	Not configura ble	Not configura ble	Not configura ble ⁷

¹ReadOnlyMany

⁷ Object storage is not consumed through OpenShift Container Platform's PVs or PVCs. Apps must integrate with the object storage REST API.



NOTE

A scaled registry is an OpenShift Container Platform registry where two or more pod replicas are running.

13.2.1. Specific application storage recommendations

² ReadWriteMany

³ Prometheus is the underlying technology used for metrics.

⁴ This does not apply to physical disk, VM physical disk, VMDK, loopback over NFS, AWS EBS, and Azure Disk.

⁵ For metrics, using file storage with the **ReadWriteMany** (RWX) access mode is unreliable. If you use file storage, do not configure the RWX access mode on any persistent volume claims (PVCs) that are configured for use with metrics.

⁶ For logging, using any shared storage would be an anti-pattern. One volume per elasticsearch is required.



IMPORTANT

Testing shows issues with using the NFS server on Red Hat Enterprise Linux (RHEL) as storage backend for core services. This includes the OpenShift Container Registry and Quay, Prometheus for monitoring storage, and Elasticsearch for logging storage. Therefore, using RHEL NFS to back PVs used by core services is not recommended.

Other NFS implementations on the marketplace might not have these issues. Contact the individual NFS implementation vendor for more information on any testing that was possibly completed against these OpenShift Container Platform core components.

13.2.1.1. Registry

In a non-scaled/high-availability (HA) OpenShift Container Platform registry cluster deployment:

- The storage technology does not have to support RWX access mode.
- The storage technology must ensure read-after-write consistency.
- The preferred storage technology is object storage followed by block storage.
- File storage is not recommended for OpenShift Container Platform registry cluster deployment with production workloads.

13.2.1.2. Scaled registry

In a scaled/HA OpenShift Container Platform registry cluster deployment:

- The storage technology must support RWX access mode.
- The storage technology must ensure read-after-write consistency.
- The preferred storage technology is object storage.
- Amazon Simple Storage Service (Amazon S3), Google Cloud Storage (GCS), Microsoft Azure Blob Storage, and OpenStack Swift are supported.
- Object storage should be S3 or Swift compliant.
- For non-cloud platforms, such as vSphere and bare metal installations, the only configurable technology is file storage.
- Block storage is not configurable.

13.2.1.3. Metrics

In an OpenShift Container Platform hosted metrics cluster deployment:

- The preferred storage technology is block storage.
- Object storage is not configurable.



IMPORTANT

It is not recommended to use file storage for a hosted metrics cluster deployment with production workloads.

13.2.1.4. Logging

In an OpenShift Container Platform hosted logging cluster deployment:

- The preferred storage technology is block storage.
- Object storage is not configurable.

13.2.1.5. Applications

Application use cases vary from application to application, as described in the following examples:

- Storage technologies that support dynamic PV provisioning have low mount time latencies, and are not tied to nodes to support a healthy cluster.
- Application developers are responsible for knowing and understanding the storage requirements for their application, and how it works with the provided storage to ensure that issues do not occur when an application scales or interacts with the storage layer.

13.2.2. Other specific application storage recommendations

- OpenShift Container Platform Internal **etcd**: For the best **etcd** reliability, the lowest consistent latency storage technology is preferable.
- It is highly recommended that you use **etcd** with storage that handles serial writes (fsync) quickly, such as NVMe or SSD. Ceph, NFS, and spinning disks are not recommended.
- Red Hat OpenStack Platform (RHOSP) Cinder: RHOSP Cinder tends to be adept in ROX access mode use cases.
- Databases: Databases (RDBMSs, NoSQL DBs, etc.) tend to perform best with dedicated block storage.

13.3. DATA STORAGE MANAGEMENT

The following table summarizes the main directories that OpenShift Container Platform components write data to.

Table 13.3. Main directories for storing OpenShift Container Platform data

Directory	Notes	Sizing	Expected growth
/var/log	Log files for all components.	10 to 30 GB.	Log files can grow quickly; size can be managed by growing disks or by using log rotate.

Directory	Notes	Sizing	Expected growth
/var/lib/etcd	Used for etcd storage when storing the database.	Less than 20 GB. Database can grow up to 8 GB.	Will grow slowly with the environment. Only storing metadata. Additional 20-25 GB for every additional 8 GB of memory.
/var/lib/containers	This is the mount point for the CRI-O runtime. Storage used for active container runtimes, including pods, and storage of local images. Not used for registry storage.	50 GB for a node with 16 GB memory. Note that this sizing should not be used to determine minimum cluster requirements. Additional 20-25 GB for every additional 8 GB of memory.	Growth is limited by capacity for running containers.
/var/lib/kubelet	Ephemeral volume storage for pods. This includes anything external that is mounted into a container at runtime. Includes environment variables, kube secrets, and data volumes not backed by persistent volumes.	Varies	Minimal if pods requiring storage are using persistent volumes. If using ephemeral storage, this can grow quickly.
/var/log	Log files for all components.	10 to 30 GB.	Log files can grow quickly; size can be managed by growing disks or by using log rotate.

CHAPTER 14. OPTIMIZING ROUTING

The OpenShift Container Platform HAProxy router scales to optimize performance.

14.1. BASELINE INGRESS CONTROLLER (ROUTER) PERFORMANCE

The OpenShift Container Platform Ingress Controller, or router, is the Ingress point for all external traffic destined for OpenShift Container Platform services.

When evaluating a single HAProxy router performance in terms of HTTP requests handled per second, the performance varies depending on many factors. In particular:

- HTTP keep-alive/close mode
- Route type
- TLS session resumption client support
- Number of concurrent connections per target route
- Number of target routes
- Back end server page size
- Underlying infrastructure (network/SDN solution, CPU, and so on)

While performance in your specific environment will vary, Red Hat lab tests on a public cloud instance of size 4 vCPU/16GB RAM. A single HAProxy router handling 100 routes terminated by backends serving 1kB static pages is able to handle the following number of transactions per second.

In HTTP keep-alive mode scenarios:

Encryption	LoadBalancerService	HostNetwork
none	21515	29622
edge	16743	22913
passthrough	36786	53295
re-encrypt	21583	25198

In HTTP close (no keep-alive) scenarios:

Encryption	LoadBalancerService	HostNetwork
none	5719	8273
edge	2729	4069
passthrough	4121	5344

Encryption	LoadBalancerService	HostNetwork
re-encrypt	2320	2941

Default Ingress Controller configuration with **ROUTER_THREADS=4** was used and two different endpoint publishing strategies (LoadBalancerService/HostNetwork) were tested. TLS session resumption was used for encrypted routes. With HTTP keep-alive, a single HAProxy router is capable of saturating 1 Gbit NIC at page sizes as small as 8 kB.

When running on bare metal with modern processors, you can expect roughly twice the performance of the public cloud instance above. This overhead is introduced by the virtualization layer in place on public clouds and holds mostly true for private cloud-based virtualization as well. The following table is a guide to how many applications to use behind the router:

Number of applications	Application type
5-10	static file/web server or caching proxy
100-1000	applications generating dynamic content

In general, HAProxy can support routes for 5 to 1000 applications, depending on the technology in use. Ingress Controller performance might be limited by the capabilities and performance of the applications behind it, such as language or static versus dynamic content.

Ingress, or router, sharding should be used to serve more routes towards applications and help horizontally scale the routing tier.

For more information on Ingress sharding, see Configuring Ingress Controller sharding by using route labels and Configuring Ingress Controller sharding by using namespace labels.

14.2. INGRESS CONTROLLER (ROUTER) PERFORMANCE OPTIMIZATIONS

OpenShift Container Platform no longer supports modifying Ingress Controller deployments by setting environment variables such as ROUTER_THREADS, ROUTER_DEFAULT_TUNNEL_TIMEOUT, ROUTER_DEFAULT_CLIENT_TIMEOUT, ROUTER_DEFAULT_SERVER_TIMEOUT, and RELOAD_INTERVAL.

You can modify the Ingress Controller deployment, but if the Ingress Operator is enabled, the configuration is overwritten.

CHAPTER 15. OPTIMIZING NETWORKING

The OpenShift SDN uses OpenvSwitch, virtual extensible LAN (VXLAN) tunnels, OpenFlow rules, and iptables. This network can be tuned by using jumbo frames, network interface cards (NIC) offloads, multi-queue, and ethtool settings.

OVN-Kubernetes uses Geneve (Generic Network Virtualization Encapsulation) instead of VXLAN as the tunnel protocol.

VXLAN provides benefits over VLANs, such as an increase in networks from 4096 to over 16 million, and layer 2 connectivity across physical networks. This allows for all pods behind a service to communicate with each other, even if they are running on different systems.

VXLAN encapsulates all tunneled traffic in user datagram protocol (UDP) packets. However, this leads to increased CPU utilization. Both these outer- and inner-packets are subject to normal checksumming rules to guarantee data is not corrupted during transit. Depending on CPU performance, this additional processing overhead can cause a reduction in throughput and increased latency when compared to traditional, non-overlay networks.

Cloud, VM, and bare metal CPU performance can be capable of handling much more than one Gbps network throughput. When using higher bandwidth links such as 10 or 40 Gbps, reduced performance can occur. This is a known issue in VXLAN-based environments and is not specific to containers or OpenShift Container Platform. Any network that relies on VXLAN tunnels will perform similarly because of the VXLAN implementation.

If you are looking to push beyond one Gbps, you can:

- Evaluate network plug-ins that implement different routing techniques, such as border gateway protocol (BGP).
- Use VXLAN-offload capable network adapters. VXLAN-offload moves the packet checksum
 calculation and associated CPU overhead off of the system CPU and onto dedicated hardware
 on the network adapter. This frees up CPU cycles for use by pods and applications, and allows
 users to utilize the full bandwidth of their network infrastructure.

VXLAN-offload does not reduce latency. However, CPU utilization is reduced even in latency tests.

15.1. OPTIMIZING THE MTU FOR YOUR NETWORK

There are two important maximum transmission units (MTUs): the network interface card (NIC) MTU and the cluster network MTU.

The NIC MTU is only configured at the time of OpenShift Container Platform installation. The MTU must be less than or equal to the maximum supported value of the NIC of your network. If you are optimizing for throughput, choose the largest possible value. If you are optimizing for lowest latency, choose a lower value.

The SDN overlay's MTU must be less than the NIC MTU by 50 bytes at a minimum. This accounts for the SDN overlay header. So, on a normal ethernet network, set this to **1450**. On a jumbo frame ethernet network, set this to **8950**.

For OVN and Geneve, the MTU must be less than the NIC MTU by 100 bytes at a minimum.



NOTE

This 50 byte overlay header is relevant to the OpenShift SDN. Other SDN solutions might require the value to be more or less.

15.2. RECOMMENDED PRACTICES FOR INSTALLING LARGE SCALE CLUSTERS

When installing large clusters or scaling the cluster to larger node counts, set the cluster network **cidr** accordingly in your **install-config.yaml** file before you install the cluster:

networking:

clusterNetwork:
- cidr: 10.128.0.0/14
hostPrefix: 23

machineCIDR: 10.0.0.0/16 networkType: OpenShiftSDN

serviceNetwork: - 172.30.0.0/16

The default cluster network **cidr 10.128.0.0/14** cannot be used if the cluster size is more than 500 nodes. It must be set to **10.128.0.0/12** or **10.128.0.0/10** to get to larger node counts beyond 500 nodes.

15.3. IMPACT OF IPSEC

Because encrypting and decrypting node hosts uses CPU power, performance is affected both in throughput and CPU usage on the nodes when encryption is enabled, regardless of the IP security system being used.

IPSec encrypts traffic at the IP payload level, before it hits the NIC, protecting fields that would otherwise be used for NIC offloading. This means that some NIC acceleration features might not be usable when IPSec is enabled and will lead to decreased throughput and increased CPU usage.

Additional resources

- Modifying advanced network configuration parameters
- Configuration parameters for the OVN-Kubernetes default CNI network provider
- Configuration parameters for the OpenShift SDN default CNI network provider

CHAPTER 16. MANAGING BARE METAL HOSTS

When you install OpenShift Container Platform on a bare metal cluster, you can provision and manage bare metal nodes using **machine** and **machineset** custom resources (CRs) for bare metal hosts that exist in the cluster.

16.1. ABOUT BARE METAL HOSTS AND NODES

To provision a Red Hat Enterprise Linux CoreOS (RHCOS) bare metal host as a node in your cluster, first create a **MachineSet** custom resource (CR) object that corresponds to the bare metal host hardware. Bare metal host machine sets describe infrastructure components specific to your configuration. You apply specific Kubernetes labels to these machine sets and then update the infrastructure components to run on only those machines.

Machine CR's are created automatically when you scale up the relevant **MachineSet** containing a **metal3.io/autoscale-to-hosts** annotation. OpenShift Container Platform uses **Machine** CR's to provision the bare metal node that corresponds to the host as specified in the **MachineSet** CR.

16.2. MAINTAINING BARE METAL HOSTS

You can maintain the details of the bare metal hosts in your cluster from the OpenShift Container Platform web console. Navigate to **Compute** → **Bare Metal Hosts**, and select a task from the **Actions** drop down menu. Here you can manage items such as BMC details, boot MAC address for the host, enable power management, and so on. You can also review the details of the network interfaces and drives for the host.

You can move a bare metal host into maintenance mode. When you move a host into maintenance mode, the scheduler moves all managed workloads off the corresponding bare metal node. No new workloads are scheduled while in maintenance mode.

You can deprovision a bare metal host in the web console. Deprovisioning a host does the following actions:

- 1. Annotates the bare metal host CR with cluster.k8s.io/delete-machine: true
- 2. Scales down the related machine set



NOTE

Powering off the host without first moving the daemon set and unmanaged static pods to another node can cause service disruption and loss of data.

Additional Resources

Adding compute machines to bare metal

16.2.1. Adding a bare metal host to the cluster using the web console

You can add bare metal hosts to the cluster in the web console.

Prerequisites

• Install an RHCOS cluster on bare metal.

• Log in as a user with **cluster-admin** privileges.

Procedure

- 1. In the web console, navigate to Compute → Bare Metal Hosts.
- 2. Select Add Host → New with Dialog.
- 3. Specify a unique name for the new bare metal host.
- 4. Set the **Boot MAC address**.
- 5. Set the Baseboard Management Console (BMC) Address
- 6. Optional: Enable power management for the host. This allows OpenShift Container Platform to control the power state of the host.
- 7. Enter the user credentials for the host's baseboard management controller (BMC).
- 8. Select to power on the host after creation, and select Create.
- Scale up the number of replicas to match the number of available bare metal hosts. Navigate to Compute → MachineSets, and increase the number of machine replicas in the cluster by selecting Edit Machine count from the Actions drop-down menu.



NOTE

You can also manage the number of bare metal nodes using the **oc scale** command and the appropriate bare metal machine set.

16.2.2. Adding a bare metal host to the cluster using YAML in the web console

You can add bare metal hosts to the cluster in the web console using a YAML file that describes the bare metal host.

Prerequisites

- Install a RHCOS compute machine on bare metal infrastructure for use in the cluster.
- Log in as a user with **cluster-admin** privileges.
- Create a **Secret** CR for the bare metal host.

Procedure

- 1. In the web console, navigate to **Compute** → **Bare Metal Hosts**.
- 2. Select Add Host → New from YAML.
- 3. Copy and paste the below YAML, modifying the relevant fields with the details of your host:

apiVersion: metal3.io/v1alpha1

kind: BareMetalHost

metadata:

name: <bare_metal_host_name>

spec:

online: true

address:
 address>

credentialsName: <secret_credentials_name> 1

disableCertificateVerification: True

bootMACAddress: <host_boot_mac_address>

hardwareProfile: unknown

1111 credentialsName must reference a valid Secret CR. The baremetal-operator cannot manage the bare metal host without a valid Secret referenced in the credentialsName. For more information about secrets and how to create them, see Understanding secrets.

- 4. Select **Create** to save the YAML and create the new bare metal host.
- Scale up the number of replicas to match the number of available bare metal hosts. Navigate to
 Compute → MachineSets, and increase the number of machines in the cluster by selecting Edit
 Machine count from the Actions drop-down menu.



NOTE

You can also manage the number of bare metal nodes using the **oc scale** command and the appropriate bare metal machine set.

16.2.3. Automatically scaling machines to the number of available bare metal hosts

To automatically create the number of **Machine** objects that matches the number of available **BareMetalHost** objects, add a **metal3.io/autoscale-to-hosts** annotation to the **MachineSet** object.

Prerequisites

- Install RHCOS bare metal compute machines for use in the cluster, and create corresponding BareMetalHost objects.
- Install the OpenShift Container Platform CLI (oc).
- Log in as a user with cluster-admin privileges.

Procedure

 Annotate the machine set that you want to configure for automatic scaling by adding the metal3.io/autoscale-to-hosts annotation. Replace <machineset> with the name of the machine set.

\$ oc annotate machineset <machineset> -n openshift-machine-api 'metal3.io/autoscale-to-hosts=<any_value>'

Wait for the new scaled machines to start.



NOTE

When you use a **BareMetalHost** object to create a machine in the cluster and labels or selectors are subsequently changed on the **BareMetalHost**, the **BareMetalHost** object continues be counted against the **MachineSet** that the **Machine** object was created from.

Additional resources

- Expanding the cluster
- MachineHealthChecks on bare metal

CHAPTER 17. WHAT HUGE PAGES DO AND HOW THEY ARE CONSUMED BY APPLICATIONS

17.1. WHAT HUGE PAGES DO

Memory is managed in blocks known as pages. On most systems, a page is 4Ki. 1Mi of memory is equal to 256 pages; 1Gi of memory is 256,000 pages, and so on. CPUs have a built-in memory management unit that manages a list of these pages in hardware. The Translation Lookaside Buffer (TLB) is a small hardware cache of virtual-to-physical page mappings. If the virtual address passed in a hardware instruction can be found in the TLB, the mapping can be determined quickly. If not, a TLB miss occurs, and the system falls back to slower, software-based address translation, resulting in performance issues. Since the size of the TLB is fixed, the only way to reduce the chance of a TLB miss is to increase the page size.

A huge page is a memory page that is larger than 4Ki. On x86_64 architectures, there are two common huge page sizes: 2Mi and 1Gi. Sizes vary on other architectures. To use huge pages, code must be written so that applications are aware of them. Transparent Huge Pages (THP) attempt to automate the management of huge pages without application knowledge, but they have limitations. In particular, they are limited to 2Mi page sizes. THP can lead to performance degradation on nodes with high memory utilization or fragmentation due to defragmenting efforts of THP, which can lock memory pages. For this reason, some applications may be designed to (or recommend) usage of pre-allocated huge pages instead of THP.

In OpenShift Container Platform, applications in a pod can allocate and consume pre-allocated huge pages.

17.2. HOW HUGE PAGES ARE CONSUMED BY APPS

Nodes must pre-allocate huge pages in order for the node to report its huge page capacity. A node can only pre-allocate huge pages for a single size.

Huge pages can be consumed through container-level resource requirements using the resource name **hugepages-<size>**, where size is the most compact binary notation using integer values supported on a particular node. For example, if a node supports 2048KiB page sizes, it exposes a schedulable resource **hugepages-2Mi**. Unlike CPU or memory, huge pages do not support over-commitment.

apiVersion: v1 kind: Pod metadata:

generateName: hugepages-volume-

spec:

containers:

 securityContext: privileged: true image: rhel7:latest command:

- sleep - inf

name: example

volumeMounts:

- mountPath: /dev/hugepages

name: hugepage

resources: limits:

hugepages-2Mi: 100Mi 1 memory: "1Gi"

cpu: "1" volumes:

- name: hugepage

emptyDir:

medium: HugePages

Specify the amount of memory for **hugepages** as the exact amount to be allocated. Do not specify this value as the amount of memory for **hugepages** multiplied by the size of the page. For example, given a huge page size of 2MB, if you want to use 100MB of huge-page-backed RAM for your application, then you would allocate 50 huge pages. OpenShift Container Platform handles the math for you. As in the above example, you can specify **100MB** directly.

Allocating huge pages of a specific size

Some platforms support multiple huge page sizes. To allocate huge pages of a specific size, precede the huge pages boot command parameters with a huge page size selection parameter **hugepagesz=<size>**. The **<size>** value must be specified in bytes with an optional scale suffix [**kKmMgG**]. The default huge page size can be defined with the **default_hugepagesz=<size>** boot parameter.

Huge page requirements

- Huge page requests must equal the limits. This is the default if limits are specified, but requests are not.
- Huge pages are isolated at a pod scope. Container isolation is planned in a future iteration.
- **EmptyDir** volumes backed by huge pages must not consume more huge page memory than the pod request.
- Applications that consume huge pages via **shmget()** with **SHM_HUGETLB** must run with a supplemental group that matches *proc/sys/vm/hugetlb_shm_group*.

Additional resources

• Configuring Transparent Huge Pages

17.3. CONSUMING HUGE PAGES RESOURCES USING THE DOWNWARD API

You can use the Downward API to inject information about the huge pages resources that are consumed by a container.

You can inject the resource allocation as environment variables, a volume plug-in, or both. Applications that you develop and run in the container can determine the resources that are available by reading the environment variables or files in the specified volumes.

Procedure

1. Create a **hugepages-volume-pod.yaml** file that is similar to the following example:

apiVersion: v1 kind: Pod

```
metadata:
 generateName: hugepages-volume-
 labels:
  app: hugepages-example
spec:
 containers:
 - securityContext:
   capabilities:
    add: ["IPC LOCK"]
  image: rhel7:latest
  command:
  - sleep
  - inf
  name: example
  volumeMounts:
  - mountPath: /dev/hugepages
   name: hugepage
  - mountPath: /etc/podinfo
   name: podinfo
  resources:
   limits:
    hugepages-1Gi: 2Gi
    memory: "1Gi"
    cpu: "1"
   requests:
    hugepages-1Gi: 2Gi
  - name: REQUESTS_HUGEPAGES_1GI <.>
   valueFrom:
    resourceFieldRef:
     containerName: example
     resource: requests.hugepages-1Gi
 volumes:
 - name: hugepage
  emptyDir:
   medium: HugePages
 - name: podinfo
  downwardAPI:
   items:
    - path: "hugepages_1G_request" <.>
     resourceFieldRef:
      containerName: example
      resource: requests.hugepages-1Gi
      divisor: 1Gi
```

- <.> Specifies to read the resource use from requests.hugepages-1Gi and expose the value as the REQUESTS_HUGEPAGES_1GI environment variable. <.> Specifies to read the resource use from requests.hugepages-1Gi and expose the value as the file /etc/podinfo/hugepages_1G_request.
- 2. Create the pod from the hugepages-volume-pod.yaml file:

\$ oc create -f hugepages-volume-pod.yaml

Verification

1. Check the value of the **REQUESTS_HUGEPAGES_1GI** environment variable:

```
$ oc exec -it $(oc get pods -l app=hugepages-example -o
jsonpath='{.items[0].metadata.name}') \
    -- env | grep REQUESTS_HUGEPAGES_1GI
```

Example output

```
REQUESTS_HUGEPAGES_1GI=2147483648
```

2. Check the value of the /etc/podinfo/hugepages_1G_request file:

```
$ oc exec -it $(oc get pods -l app=hugepages-example -o
jsonpath='{.items[0].metadata.name}') \
    -- cat /etc/podinfo/hugepages_1G_request
```

Example output

2

Additional resources

• Allowing containers to consume Downward API objects

17.4. CONFIGURING HUGE PAGES

Nodes must pre-allocate huge pages used in an OpenShift Container Platform cluster. There are two ways of reserving huge pages: at boot time and at run time. Reserving at boot time increases the possibility of success because the memory has not yet been significantly fragmented. The Node Tuning Operator currently supports boot time allocation of huge pages on specific nodes.

17.4.1. At boot time

Procedure

To minimize node reboots, the order of the steps below needs to be followed:

1. Label all nodes that need the same huge pages setting by a label.

\$ oc label node <node_using_hugepages> node-role.kubernetes.io/worker-hp=

2. Create a file with the following content and name it hugepages-tuned-boottime.yaml:

```
apiVersion: tuned.openshift.io/v1
kind: Tuned
metadata:
name: hugepages 1
namespace: openshift-cluster-node-tuning-operator
spec:
profile: 2
- data: |
[main]
```

```
summary=Boot time configuration for hugepages
include=openshift-node
[bootloader]
cmdline_openshift_node_hugepages=hugepagesz=2M hugepages=50
name: openshift-node-hugepages

recommend:
- machineConfigLabels: 4
    machineconfiguration.openshift.io/role: "worker-hp"
priority: 30
profile: openshift-node-hugepages
```

- Set the **name** of the Tuned resource to **hugepages**.
- Set the **profile** section to allocate huge pages.
- 3 Note the order of parameters is important as some platforms support huge pages of various sizes.
- Enable machine config pool based matching.
- 3. Create the Tuned hugepages object
 - \$ oc create -f hugepages-tuned-boottime.yaml
- 4. Create a file with the following content and name it **hugepages-mcp.yaml**:

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfigPool
metadata:
name: worker-hp
labels:
worker-hp: ""
spec:
machineConfigSelector:
matchExpressions:
- {key: machineconfiguration.openshift.io/role, operator: In, values: [worker,worker-hp]}
nodeSelector:
matchLabels:
node-role.kubernetes.io/worker-hp: ""
```

5. Create the machine config pool:

\$ oc create -f hugepages-mcp.yaml

Given enough non-fragmented memory, all the nodes in the **worker-hp** machine config pool should now have 50 2Mi huge pages allocated.

\$ oc get node <node_using_hugepages> -o jsonpath="{.status.allocatable.hugepages-2Mi}" 100Mi



WARNING

This functionality is currently only supported on Red Hat Enterprise Linux CoreOS (RHCOS) 8.x worker nodes. On Red Hat Enterprise Linux (RHEL) 7.x worker nodes the TuneD **[bootloader]** plug-in is currently not supported.

CHAPTER 18. PERFORMANCE ADDON OPERATOR FOR LOW LATENCY NODES

18.1. UNDERSTANDING LOW LATENCY

The emergence of Edge computing in the area of Telco / 5G plays a key role in reducing latency and congestion problems and improving application performance.

Simply put, latency determines how fast data (packets) moves from the sender to receiver and returns to the sender after processing by the receiver. Obviously, maintaining a network architecture with the lowest possible delay of latency speeds is key for meeting the network performance requirements of 5G. Compared to 4G technology, with an average latency of 50ms, 5G is targeted to reach latency numbers of 1ms or less. This reduction in latency boosts wireless throughput by a factor of 10.

Many of the deployed applications in the Telco space require low latency that can only tolerate zero packet loss. Tuning for zero packet loss helps mitigate the inherent issues that degrade network performance. For more information, see Tuning for Zero Packet Loss in Red Hat OpenStack Platform (RHOSP).

The Edge computing initiative also comes in to play for reducing latency rates. Think of it as literally being on the edge of the cloud and closer to the user. This greatly reduces the distance between the user and distant data centers, resulting in reduced application response times and performance latency.

Administrators must be able to manage their many Edge sites and local services in a centralized way so that all of the deployments can run at the lowest possible management cost. They also need an easy way to deploy and configure certain nodes of their cluster for real-time low latency and high-performance purposes. Low latency nodes are useful for applications such as Cloud-native Network Functions (CNF) and Data Plane Development Kit (DPDK).

OpenShift Container Platform currently provides mechanisms to tune software on an OpenShift Container Platform cluster for real-time running and low latency (around <20 microseconds reaction time). This includes tuning the kernel and OpenShift Container Platform set values, installing a kernel, and reconfiguring the machine. But this method requires setting up four different Operators and performing many configurations that, when done manually, is complex and could be prone to mistakes.

OpenShift Container Platform provides a Performance Addon Operator to implement automatic tuning to achieve low latency performance for OpenShift applications. The cluster administrator uses this performance profile configuration that makes it easier to make these changes in a more reliable way. The administrator can specify whether to update the kernel to kernel-rt, reserve CPUs for cluster and operating system housekeeping duties, including pod infra containers, and isolate CPUs for application containers to run the workloads.

18.1.1. About hyperthreading for low latency and real-time applications

Hyperthreading is an Intel processor technology that allows a physical CPU processor core to function as two logical cores, executing two independent threads simultaneously. Hyperthreading allows for better system throughput for certain workload types where parallel processing is beneficial. The default OpenShift Container Platform configuration expects hyperthreading to be enabled by default.

For telecommunications applications, it is important to design your application infrastructure to minimize latency as much as possible. Hyperthreading can slow performance times and negatively affect throughput for compute intensive workloads that require low latency. Disabling hyperthreading ensures predictable performance and can decrease processing times for these workloads.



NOTE

Hyperthreading implementation and configuration differs depending on the hardware you are running OpenShift Container Platform on. Consult the relevant host hardware tuning information for more details of the hyperthreading implementation specific to that hardware. Disabling hyperthreading can increase the cost per core of the cluster.

Additional resources

• Configuring hyperthreading for a cluster

18.2. INSTALLING THE PERFORMANCE ADDON OPERATOR

Performance Addon Operator provides the ability to enable advanced node performance tunings on a set of nodes. As a cluster administrator, you can install Performance Addon Operator using the OpenShift Container Platform CLI or the web console.

18.2.1. Installing the Operator using the CLI

As a cluster administrator, you can install the Operator using the CLI.

Prerequisites

- A cluster installed on bare-metal hardware.
- Install the OpenShift CLI (oc).
- Log in as a user with **cluster-admin** privileges.

Procedure

- 1. Create a namespace for the Performance Addon Operator by completing the following actions:
 - a. Create the following Namespace Custom Resource (CR) that defines the openshift-performance-addon-operator namespace, and then save the YAML in the paonamespace.yaml file:

apiVersion: v1 kind: Namespace metadata: name: openshift-performance-addon-operator annotations: workload.openshift.io/allowed: management labels: openshift.io/run-level: "1"

b. Create the namespace by running the following command:

\$ oc create -f pao-namespace.yaml

2. Install the Performance Addon Operator in the namespace you created in the previous step by creating the following objects:

a. Create the following **OperatorGroup** CR and save the YAML in the **pao-operatorgroup.yaml** file:

apiVersion: operators.coreos.com/v1

kind: OperatorGroup

metadata:

name: openshift-performance-addon-operator namespace: openshift-performance-addon-operator

b. Create the **OperatorGroup** CR by running the following command:

\$ oc create -f pao-operatorgroup.yaml

c. Run the following command to get the **channel** value required for the next step.

\$ oc get packagemanifest performance-addon-operator -n openshift-marketplace -o jsonpath='{.status.defaultChannel}'

Example output

4.8

d. Create the following Subscription CR and save the YAML in the pao-sub.yaml file:

Example Subscription

apiVersion: operators.coreos.com/v1alpha1

kind: Subscription

metadata:

name: openshift-performance-addon-operator-subscription

namespace: openshift-performance-addon-operator

spec:

channel: "<channel>"

name: performance-addon-operator

source: redhat-operators 2

sourceNamespace: openshift-marketplace

- Specify the value from you obtained in the previous step for the .status.defaultChannel parameter.
- You must specify the **redhat-operators** value.
- e. Create the Subscription object by running the following command:

\$ oc create -f pao-sub.yaml

f. Change to the openshift-performance-addon-operator project:

\$ oc project openshift-performance-addon-operator

18.2.2. Installing the Performance Addon Operator using the web console

As a cluster administrator, you can install the Performance Addon Operator using the web console.



NOTE

You must create the **Namespace** CR and **OperatorGroup** CR as mentioned in the previous section.

Procedure

- 1. Install the Performance Addon Operator using the OpenShift Container Platform web console:
 - a. In the OpenShift Container Platform web console, click **Operators** → **OperatorHub**.
 - b. Choose **Performance Addon Operator** from the list of available Operators, and then click **Install**.
 - c. On the Install Operator page, select All namespaces on the cluster. Then, click Install.
- 2. Optional: Verify that the performance-addon-operator installed successfully:
 - a. Switch to the **Operators** → **Installed Operators** page.
 - b. Ensure that **Performance Addon Operator** is listed in the **openshift-performance-addon-operator** project with a **Status** of **InstallSucceeded**.



NOTE

During installation an Operator might display a **Failed** status. If the installation later succeeds with an **InstallSucceeded** message, you can ignore the **Failed** message.

If the Operator does not appear as installed, to troubleshoot further:

- Go to the Operators → Installed Operators page and inspect the Operator Subscriptions and Install Plans tabs for any failure or errors under Status.
- Go to the Workloads → Pods page and check the logs for pods in the performanceaddon-operator project.

18.3. UPGRADING PERFORMANCE ADDON OPERATOR

You can manually upgrade to the next minor version of Performance Addon Operator and monitor the status of an update by using the web console.

18.3.1. About upgrading Performance Addon Operator

- You can upgrade to the next minor version of Performance Addon Operator by using the OpenShift Container Platform web console to change the channel of your Operator subscription.
- You can enable automatic z-stream updates during Performance Addon Operator installation.
- Updates are delivered via the Marketplace Operator, which is deployed during OpenShift Container Platform installation. The Marketplace Operator makes external Operators available to your cluster.

• The amount of time an update takes to complete depends on your network connection. Most automatic updates complete within fifteen minutes.

18.3.1.1. How Performance Addon Operator upgrades affect your cluster

- Neither the low latency tuning nor huge pages are affected.
- Updating the Operator should not cause any unexpected reboots.

18.3.1.2. Upgrading Performance Addon Operator to the next minor version

You can manually upgrade Performance Addon Operator to the next minor version by using the OpenShift Container Platform web console to change the channel of your Operator subscription.

Prerequisites

• Access to the cluster as a user with the cluster-admin role.

Procedure

- 1. Access the web console and navigate to **Operators** → **Installed Operators**.
- 2. Click Performance Addon Operator to open the Operator details page.
- 3. Click the **Subscription** tab to open the **Subscription details** page.
- 4. In the **Update channel** pane, click the pencil icon on the right side of the version number to open the **Change Subscription update channel** window.
- 5. Select the next minor version. For example, if you want to upgrade to Performance Addon Operator 4.8, select **4.8**.
- 6. Click Save.
- 7. Check the status of the upgrade by navigating to **Operators** → **Installed Operators**. You can also check the status by running the following **oc** command:
 - \$ oc get csv -n openshift-performance-addon-operator

18.3.1.3. Upgrading Performance Addon Operator when previously installed to a specific namespace

If you previously installed the Performance Addon Operator to a specific namespace on the cluster, for example **openshift-performance-addon-operator**, modify the **OperatorGroup** object to remove the **targetNamespaces** entry before upgrading.

Prerequisites

- Install the OpenShift Container Platform CLI (oc).
- Log in to the OpenShift cluster as a user with cluster-admin privileges.

Procedure

1. Edit the Performance Addon Operator **OperatorGroup** CR and remove the **spec** element that contains the **targetNamespaces** entry by running the following command:

\$ oc patch operatorgroup -n openshift-performance-addon-operator openshift-performance-addon-operator --type json -p '[{ "op": "remove", "path": "/spec" }]'

- 2. Wait until the Operator Lifecycle Manager (OLM) processes the change.
- 3. Verify that the OperatorGroup CR change has been successfully applied. Check that the **OperatorGroup** CR **spec** element has been removed:

\$ oc describe -n openshift-performance-addon-operator og openshift-performance-addon-operator

4. Proceed with the Performance Addon Operator upgrade.

18.3.2. Monitoring upgrade status

The best way to monitor Performance Addon Operator upgrade status is to watch the **ClusterServiceVersion** (CSV) **PHASE**. You can also monitor the CSV conditions in the web console or by running the **oc get csv** command.



NOTE

The **PHASE** and conditions values are approximations that are based on available information.

Prerequisites

- Access to the cluster as a user with the **cluster-admin** role.
- Install the OpenShift CLI (oc).

Procedure

1. Run the following command:

\$ oc get csv

2. Review the output, checking the **PHASE** field. For example:

VERSION REPLACES PHASE
4.8.0 performance-addon-operator.v4.8.0 Installing
4.7.0 Replacing

3. Run **get csv** again to verify the output:

oc get csv

Example output

NAME DISPLAY VERSION REPLACES PHASE

performance-addon-operator.v4.8.0 Performance Addon Operator 4.8.0 performance-addon-operator.v4.7.0 Succeeded

18.4. PROVISIONING REAL-TIME AND LOW LATENCY WORKLOADS

Many industries and organizations need extremely high performance computing and might require low and predictable latency, especially in the financial and telecommunications industries. For these industries, with their unique requirements, OpenShift Container Platform provides a Performance Addon Operator to implement automatic tuning to achieve low latency performance and consistent response time for OpenShift Container Platform applications.

The cluster administrator can use this performance profile configuration to make these changes in a more reliable way. The administrator can specify whether to update the kernel to kernel-rt (real-time), reserve CPUs for cluster and operating system housekeeping duties, including pod infra containers, and isolate CPUs for application containers to run the workloads.

18.4.1. Known limitations for real-time



NOTE

The RT kernel is only supported on worker nodes.

To fully utilize the real-time mode, the containers must run with elevated privileges. See Set capabilities for a Container for information on granting privileges.

OpenShift Container Platform restricts the allowed capabilities, so you might need to create a **SecurityContext** as well.



NOTE

This procedure is fully supported with bare metal installations using Red Hat Enterprise Linux CoreOS (RHCOS) systems.

Establishing the right performance expectations refers to the fact that the real-time kernel is not a panacea. Its objective is consistent, low-latency determinism offering predictable response times. There is some additional kernel overhead associated with the real-time kernel. This is due primarily to handling hardware interruptions in separately scheduled threads. The increased overhead in some workloads results in some degradation in overall throughput. The exact amount of degradation is very workload dependent, ranging from 0% to 30%. However, it is the cost of determinism.

18.4.2. Provisioning a worker with real-time capabilities

- 1. Install Performance Addon Operator to the cluster.
- 2. Optional: Add a node to the OpenShift Container Platform cluster. See Setting BIOS parameters.
- 3. Optional: Create a new machine config pool for real-time nodes.
- 4. Add the node to the proper machine config pool, using node role labels.

 You must decide which nodes will be configured with real-time workloads. It could be all of the nodes in the cluster or a subset of the nodes. The Performance Addon Operator expects all of the nodes are part of a dedicated machine config pool. If you use all of the nodes, you just point

the Performance Addon Operator to the worker node role label. If you use a subset, you must group the nodes into a new machine config pool.

- 5. Create the **PerformanceProfile** with the proper set of housekeeping cores and **realTimeKernel: enabled: true**.
- 6. Specify a node selector in the **PerformanceProfile**, as shown here:

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: example-performanceprofile spec: ... realTimeKernel: enabled: true nodeSelector: node-role.kubernetes.io/worker-rt: ""

7. Verify that a matching machine config pool exists with a label:

machineconfiguration.openshift.io/role=worker-rt

- 8. OpenShift Container Platform will start configuring the nodes, which might involve multiple reboots. Wait for the nodes to settle. This can take a long time depending on the specific hardware you use, but 20 minutes per node is expected.
- 9. Verify everything is working as expected.

18.4.3. Verifying the real-time kernel installation

Use this command to verify that the real-time kernel is installed:

\$ oc get node -o wide

Note the worker with the role worker-rt that contains the string 4.18.0-211.rt5.23.el8.x86_64:

NAME STATUS ROLES AGE VERSION INTERNAL-IP EXTERNAL-IP OS-IMAGE KERNEL-VERSION CONTAINER-RUNTIME cnf-worker-0.example.com Ready worker,worker-rt 5d17h v1.21.0 128.66.135.107 <none> Red Hat Enterprise Linux CoreOS 46.82.202008252340-0 (Ootpa) 4.18.0-211.rt5.23.el8.x86_64 cri-o://1.21.0-90.rhaos4.8.git4a0ac05.el8-rc.1 [...]

18.4.4. Creating a workload that works in real-time

Use the following procedures for preparing a workload that will use real-time capabilities.

Procedure

- 1. Create a pod with a QoS class of **Guaranteed**.
- 2. Optional: Disable CPU load balancing for DPDK.

3. Assign a proper node selector.

When writing your applications, follow the general recommendations described in Application tuning and deployment.

18.4.5. Creating a pod with a QoS class of Guaranteed

Keep the following in mind when you create a pod that is given a QoS class of **Guaranteed**:

- Every container in the pod must have a memory limit and a memory request, and they must be the same.
- Every container in the pod must have a CPU limit and a CPU request, and they must be the same.

The following example shows the configuration file for a pod that has one container. The container has a memory limit and a memory request, both equal to 200 MiB. The container has a CPU limit and a CPU request, both equal to 1 CPU.

```
apiVersion: v1
kind: Pod
metadata:
 name: gos-demo
 namespace: qos-example
spec:
 containers:
 - name: gos-demo-ctr
  image: <image-pull-spec>
  resources:
   limits:
    memory: "200Mi"
    cpu: "1"
   requests:
    memory: "200Mi"
    cpu: "1"
```

1. Create the pod:

```
$ oc apply -f gos-pod.yaml --namespace=gos-example
```

2. View detailed information about the pod:

```
$ oc get pod qos-demo --namespace=qos-example --output=yaml
```

Example output

```
spec:
containers:
...
status:
qosClass: Guaranteed
```



NOTE

If a container specifies its own memory limit, but does not specify a memory request, OpenShift Container Platform automatically assigns a memory request that matches the limit. Similarly, if a container specifies its own CPU limit, but does not specify a CPU request, OpenShift Container Platform automatically assigns a CPU request that matches the limit.

18.4.6. Optional: Disabling CPU load balancing for DPDK

Functionality to disable or enable CPU load balancing is implemented on the CRI-O level. The code under the CRI-O disables or enables CPU load balancing only when the following requirements are met.

• The pod must use the **performance-<profile-name>** runtime class. You can get the proper name by looking at the status of the performance profile, as shown here:

```
apiVersion: performance.openshift.io/v2 kind: PerformanceProfile ... status: ... runtimeClass: performance-manual
```

• The pod must have the **cpu-load-balancing.crio.io: true** annotation.

The Performance Addon Operator is responsible for the creation of the high-performance runtime handler config snippet under relevant nodes and for creation of the high-performance runtime class under the cluster. It will have the same content as default runtime handler except it enables the CPU load balancing configuration functionality.

To disable the CPU load balancing for the pod, the **Pod** specification must include the following fields:

```
apiVersion: v1
kind: Pod
metadata:
...
annotations:
...
cpu-load-balancing.crio.io: "disable"
...
...
spec:
...
runtimeClassName: performance-<profile_name>
...
```



NOTE

Only disable CPU load balancing when the CPU manager static policy is enabled and for pods with guaranteed QoS that use whole CPUs. Otherwise, disabling CPU load balancing can affect the performance of other containers in the cluster.

18.4.7. Assigning a proper node selector

The preferred way to assign a pod to nodes is to use the same node selector the performance profile used, as shown here:

```
apiVersion: v1
kind: Pod
metadata:
name: example
spec:
[...]
nodeSelector:
node-role.kubernetes.io/worker-rt: ""
```

For more information, see Placing pods on specific nodes using node selectors .

18.4.8. Scheduling a workload onto a worker with real-time capabilities

Use label selectors that match the nodes attached to the machine config pool that was configured for low latency by the Performance Addon Operator. For more information, see Assigning pods to nodes.

18.4.9. Managing device interrupt processing for guaranteed pod isolated CPUs

The Performance Addon Operator can manage host CPUs by dividing them into reserved CPUs for cluster and operating system housekeeping duties, including pod infra containers, and isolated CPUs for application containers to run the workloads. This allows you to set CPUs for low latency workloads as isolated.

Device interrupts are load balanced between all isolated and reserved CPUs to avoid CPUs being overloaded, with the exception of CPUs where there is a guaranteed pod running. Guaranteed pod CPUs are prevented from processing device interrupts when the relevant annotations are set for the pod.

In the performance profile, **globallyDisableIrqLoadBalancing** is used to manage whether device interrupts are processed or not. For certain workloads the reserved CPUs are not always sufficient for dealing with device interrupts, and for this reason, device interrupts are not globally disabled on the isolated CPUs. By default, Performance Addon Operator does not disable device interrupts on isolated CPUs.

To achieve low latency for workloads, some (but not all) pods require the CPUs they are running on to not process device interrupts. A pod annotation, **irq-load-balancing.crio.io**, is used to define whether device interrupts are processed or not. When configured, CRI-O disables device interrupts only as long as the pod is running.

18.4.9.1. Disabling global device interrupts handling in Performance Addon Operator

To configure Performance Addon Operator to disable global device interrupts for the isolated CPU set, set the **globallyDisableIrqLoadBalancing** field in the performance profile to **true**. When **true**, conflicting pod annotations are ignored. When **false**, IRQ loads are balanced across all CPUs.

A performance profile snippet illustrates this setting:

apiVersion: performance.openshift.io/v2

kind: PerformanceProfile

metadata: name: manual

```
spec:
globallyDisableIrqLoadBalancing: true
...
```

18.4.9.2. Disabling interrupt processing for individual pods

To disable interrupt processing for individual pods, ensure that **globallyDisableIrqLoadBalancing** is set to **false** in the performance profile. Then, in the pod specification, set the **irq-load-balancing.crio.io** and **cpu-load-balancing.crio.io** pod annotations to **disable**. An example pod specification snippet that illustrates this is below:

```
apiVersion: performance.openshift.io/v2
kind: Pod
metadata:
annotations:
irq-load-balancing.crio.io: "disable"
cpu-load-balancing.crio.io: "disable"
spec:
runtimeClassName: performance-<profile_name>...
```

18.4.10. Upgrading the performance profile to use device interrupt processing

When you upgrade the Performance Addon Operator performance profile custom resource definition (CRD) from v1 or v1alpha1 to v2, **globallyDisableIrqLoadBalancing** is set to **true** on existing profiles.



NOTE

When **globallyDisableIrqLoadBalancing** is set to **true**, device interrupts are processed across all CPUs as long as they don't belong to a guaranteed pod.

18.4.10.1. Supported API Versions

The Performance Addon Operator supports **v2**, **v1**, and **v1alpha1** for the performance profile **apiVersion** field. The v1 and v1alpha1 APIs are identical. The v2 API includes an optional boolean field **globallyDisableIrqLoadBalancing** with a default value of **false**.

18.4.10.1.1. Upgrading Performance Addon Operator API from v1alpha1 to v1

When upgrading Performance Addon Operator API version from v1alpha1 to v1, the v1alpha1 performance profiles are converted on-the-fly using a "None" Conversion strategy and served to the Performance Addon Operator with API version v1.

18.4.10.1.2. Upgrading Performance Addon Operator API from v1alpha1 or v1 to v2

When upgrading from an older Performance Addon Operator API version, the existing v1 and v1alpha1 performance profiles are converted using a conversion webhook that injects the **globallyDisableIrqLoadBalancing** field with a value of **true**.

18.4.11. Configuring a node for IRQ dynamic load balancing

To configure a cluster node to handle IRQ dynamic load balancing, do the following:

- 1. Log in to the OpenShift Container Platform cluster as a user with cluster-admin privileges.
- 2. Set the performance profile apiVersion to use performance.openshift.io/v2.
- 3. Remove the **globallyDisableIrqLoadBalancing** field or set it to **false**.
- 4. Set the appropriate isolated and reserved CPUs. The following snippet illustrates a profile that reserves 2 CPUs. IRQ load-balancing is enabled for pods running on the **isolated** CPU set:

```
apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: dynamic-irq-profile spec: cpu: isolated: 2-5 reserved: 0-1 ...
```



NOTE

When you configure reserved and isolated CPUs, the infra containers in pods use the reserved CPUs and the application containers use the isolated CPUs.

5. Create the pod that uses exclusive CPUs, and set **irq-load-balancing.crio.io** and **cpu-quota.crio.io** annotations to **disable**. For example:

```
apiVersion: v1
kind: Pod
metadata:
 name: dynamic-irq-pod
 annotations:
   irq-load-balancing.crio.io: "disable"
   cpu-quota.crio.io: "disable"
spec:
 containers:
 - name: dynamic-irq-pod
  image: "quay.io/openshift-kni/cnf-tests:4.8"
  command: ["sleep", "10h"]
  resources:
   requests:
    cpu: 2
    memory: "200M"
   limits:
    cpu: 2
    memory: "200M"
 nodeSelector:
  node-role.kubernetes.io/worker-cnf: ""
 runtimeClassName: performance-dynamic-irq-profile
```

6. Enter the pod **runtimeClassName** in the form performance-rofile_name>, where
cprofile_name> is the **name** from the **PerformanceProfile** YAML, in this example, **performance-dynamic-irq-profile**.

- 7. Set the node selector to target a cnf-worker.
- 8. Ensure the pod is running correctly. Status should be **running**, and the correct cnf-worker node should be set:

\$ oc get pod -o wide

Expected output

NAME READY STATUS RESTARTS AGE IP NODE

NOMINATED NODE READINESS GATES

dynamic-irq-pod 1/1 Running 0 5h33m <ip-address> <node-name> <none>

9. Get the CPUs that the pod configured for IRQ dynamic load balancing runs on:

\$ oc exec -it dynamic-irq-pod -- /bin/bash -c "grep Cpus_allowed_list /proc/self/status | awk '{print \$2}'"

Expected output

Cpus_allowed_list: 2-3

10. Ensure the node configuration is applied correctly. SSH into the node to verify the configuration.

\$ oc debug node/<node-name>

Expected output

Starting pod/<node-name>-debug ...
To use host binaries, run `chroot /host`

Pod IP: <ip-address>

If you don't see a command prompt, try pressing enter.

sh-4.4#

11. Verify that you can use the node file system:

sh-4.4# chroot /host

Expected output

sh-4.4#

12. Ensure the default system CPU affinity mask does not include the **dynamic-irq-pod** CPUs, for example, CPUs 2 and 3.

\$ cat /proc/irq/default_smp_affinity

Example output

33

13. Ensure the system IRQs are not configured to run on the **dynamic-irq-pod** CPUs:

find /proc/irq/ -name smp_affinity_list -exec sh -c 'i="\$1"; mask= $(cat \ i)$; file= $(echo \ i)$; echo $file: \mask' _ {} \$

Example output

```
/proc/irq/0/smp affinity list: 0-5
/proc/irq/1/smp_affinity_list: 5
/proc/irq/2/smp_affinity_list: 0-5
/proc/irq/3/smp_affinity_list: 0-5
/proc/irq/4/smp affinity list: 0
/proc/irq/5/smp affinity list: 0-5
/proc/irq/6/smp_affinity_list: 0-5
/proc/irq/7/smp_affinity_list: 0-5
/proc/irq/8/smp affinity list: 4
/proc/irq/9/smp affinity list: 4
/proc/irq/10/smp affinity list: 0-5
/proc/irq/11/smp_affinity_list: 0
/proc/irq/12/smp_affinity_list: 1
/proc/irg/13/smp affinity list: 0-5
/proc/irq/14/smp_affinity_list: 1
/proc/irq/15/smp_affinity_list: 0
/proc/irq/24/smp_affinity_list: 1
/proc/irg/25/smp affinity list: 1
/proc/irq/26/smp affinity list: 1
/proc/irq/27/smp_affinity_list: 5
/proc/irq/28/smp_affinity_list: 1
/proc/irq/29/smp_affinity_list: 0
/proc/irq/30/smp affinity list: 0-5
```

Some IRQ controllers do not support IRQ re-balancing and will always expose all online CPUs as the IRQ mask. These IRQ controllers effectively run on CPU 0. For more information on the host configuration, SSH into the host and run the following, replacing **<irq-num>** with the CPU number that you want to query:

\$ cat /proc/irq/<irq-num>/effective_affinity

18.4.12. Configuring hyperthreading for a cluster

To configure hyperthreading for an OpenShift Container Platform cluster, set the CPU threads in the performance profile to the same cores that are configured for the reserved or isolated CPU pools.



NOTE

If you configure a performance profile, and subsequently change the hyperthreading configuration for the host, ensure that you update the CPU **isolated** and **reserved** fields in the **PerformanceProfile** YAML to match the new configuration.



WARNING

Disabling a previously enabled host hyperthreading configuration can cause the CPU core IDs listed in the **PerformanceProfile** YAML to be incorrect. This incorrect configuration can cause the node to become unavailable because the listed CPUs can no longer be found.

Prerequisites

- Access to the cluster as a user with the **cluster-admin** role.
- Install the OpenShift CLI (oc).

Procedure

1. Ascertain which threads are running on what CPUs for the host you want to configure. You can view which threads are running on the host CPUs by logging in to the cluster and running the following command:

\$ Iscpu --all --extended

Example output

```
CPU NODE SOCKET CORE L1d:L1i:L2:L3 ONLINE MAXMHZ MINMHZ
0 0
        0:0:0:0
                   yes 4800.0000 400.0000
                    yes 4800.0000 400.0000
        1 1:1:1:0
1
  0
2 0 0 2 2:2:2:0 yes 4800.0000 400.0000
3 0 0 3 3:3:3:0
                    yes 4800.0000 400.0000
4
 0 0 0:0:0:0 yes 4800.0000 400.0000
5
 0 0
       1 1:1:1:0
                    yes 4800.0000 400.0000
6
                    yes 4800.0000 400.0000
  0
        2 2:2:2:0
7
         3 3:3:3:0
                    yes 4800.0000 400.0000
```

In this example, there are eight logical CPU cores running on four physical CPU cores. CPU0 and CPU4 are running on physical Core0, CPU1 and CPU5 are running on physical Core 1, and so on.

Alternatively, to view the threads that are set for a particular physical CPU core (**cpu0** in the example below), open a command prompt and run the following:

\$ cat /sys/devices/system/cpu/cpu0/topology/thread_siblings_list

Example output

0-4

2. Apply the isolated and reserved CPUs in the **PerformanceProfile** YAML. For example, you could set logical cores CPU0 and CPU4 as **isolated**, and logical cores CPU1 and CPU5 as **reserved**. When you configure reserved and isolated CPUs, the infra containers in pods use the

reserved CPUs and the application containers use the isolated CPUs.

```
...
cpu:
isolated: 0-4
reserved: 1-5
```



IMPORTANT

Hyperthreading is enabled by default on most Intel processors. If you enable hyperthreading, all threads processed by a particular core must be isolated or processed on the same core.

18.4.12.1. Disabling hyperthreading for low latency applications

When configuring clusters for low latency processing, consider whether you want to disable hyperthreading before you deploy the cluster. To disable hyperthreading, do the following:

- 1. Create a performance profile that is appropriate for your hardware and topology.
- 2. Set **nosmt** as an additional kernel argument. The following example performance profile illustrates this setting:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 name: example-performanceprofile
 additionalKernelArgs:
  - nmi watchdog=0
  - audit=0
  - mce=off
  - processor.max_cstate=1
  - idle=poll
  - intel_idle.max_cstate=0
  - nosmt
 cpu:
  isolated: 2-3
  reserved: 0-1
 hugepages:
  defaultHugepagesSize: 1G
  pages:
   - count: 2
    node: 0
    size: 1G
 nodeSelector:
  node-role.kubernetes.io/performance: "
 realTimeKernel:
  enabled: true
```



NOTE

When you configure reserved and isolated CPUs, the infra containers in pods use the reserved CPUs and the application containers use the isolated CPUs.

18.5. TUNING NODES FOR LOW LATENCY WITH THE PERFORMANCE PROFILE

The performance profile lets you control latency tuning aspects of nodes that belong to a certain machine config pool. After you specify your settings, the **PerformanceProfile** object is compiled into multiple objects that perform the actual node level tuning:

- A **MachineConfig** file that manipulates the nodes.
- A KubeletConfig file that configures the Topology Manager, the CPU Manager, and the OpenShift Container Platform nodes.
- The Tuned profile that configures the Node Tuning Operator.

You can use a performance profile to specify whether to update the kernel to kernel-rt, to allocate huge pages, and to partition the CPUs for performing housekeeping duties or running workloads.

Sample performance profile

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: performance spec: cpu: isolated: "5-15" 1 reserved: "0-4" 2 hugepages: defaultHugepagesSize: "1G" pages: - size: "1G" count: 16 node: 0 realTimeKernel: enabled: true (3) numa: 4 topologyPolicy: "best-effort" nodeSelector:

node-role.kubernetes.io/worker-cnf: "" 5

- Use this field to isolate specific CPUs to use with application containers for workloads.
- Use this field to reserve specific CPUs to use with infra containers for housekeeping.
- Use this field to install the real-time kernel on the node. Valid values are **true** or **false**. Setting the **true** value installs the real-time kernel.
- Use this field to configure the topology manager policy. Valid values are **none** (default), **best-effort**, **restricted**, and **single-numa-node**. For more information, see Topology Manager Policies.



Use this field to specify a node selector to apply the performance profile to specific nodes.

18.5.1. Configuring huge pages

Nodes must pre-allocate huge pages used in an OpenShift Container Platform cluster. Use the Performance Addon Operator to allocate huge pages on a specific node.

OpenShift Container Platform provides a method for creating and allocating huge pages. Performance Addon Operator provides an easier method for doing this using the performance profile.

For example, in the **hugepages pages** section of the performance profile, you can specify multiple blocks of **size**, **count**, and, optionally, **node**:

hugepages:

defaultHugepagesSize: "1G"

pages:
- size: "1G"
count: 4
node: 0 1



node is the NUMA node in which the huge pages are allocated. If you omit **node**, the pages are evenly spread across all NUMA nodes.



NOTE

Wait for the relevant machine config pool status that indicates the update is finished.

These are the only configuration steps you need to do to allocate huge pages.

Verification

- To verify the configuration, see the /proc/meminfo file on the node:
 - \$ oc debug node/ip-10-0-141-105.ec2.internal
 - # grep -i huge /proc/meminfo

Example output

AnonHugePages: ##### ##
ShmemHugePages: 0 kB
HugePages_Total: 2
HugePages_Free: 2
HugePages_Rsvd: 0
HugePages_Surp: 0
Hugepagesize: #####
Hugetlb: ######

Use oc describe to report the new size:

\$ oc describe node worker-0.ocp4poc.example.com | grep -i huge

Example output

hugepages-1g=true

hugepages-###: ### hugepages-###: ###

18.5.2. Allocating multiple huge page sizes

You can request huge pages with different sizes under the same container. This allows you to define more complicated pods consisting of containers with different huge page size needs.

For example, you can define sizes **1G** and **2M** and the Performance Addon Operator will configure both sizes on the node, as shown here:

spec:

hugepages:

defaultHugepagesSize: 1G

pages: - count: 1024

node: 0 size: 2M - count: 4 node: 1 size: 1G

18.5.3. Restricting CPUs for infra and application containers

You can reserve cores (threads) from a single NUMA node for operating system housekeeping tasks and put your workloads on another NUMA node. Partitioning the CPUs this way can prevent the housekeeping processes from impacting latency-sensitive application processes. By default, CRI-O uses all online CPUs to run infra containers on nodes, which can result in context switches and spikes in latency.

You can ensure that housekeeping tasks and workloads run on separate NUMA nodes by specifying two groups of CPUs in the **spec** section of the performance profile.

- **isolated** The CPUs for the application container workloads. These CPUs have the lowest latency. Processes in this group have no interruptions and can, for example, reach much higher DPDK zero packet loss bandwidth.
- reserved The CPUs for the cluster and operating system housekeeping duties, including pod infra containers. Threads in the reserved group tend to be very busy, so latency-sensitive applications should be run in the isolated group. See Create a pod that gets assigned a QoS class of Guaranteed.

Procedure

- 1. Create a performance profile that is appropriate for your hardware and topology.
- 2. Add the **reserved** and **isolated** parameters with the CPUs you want reserved and isolated for the infra and application containers:

apiVersion: performance.openshift.io/v2

kind: PerformanceProfile metadata:

name: infra-cpus

spec: cpu:

reserved: "0-4,9" 1 isolated: "5-8" 2 nodeSelector: 3

node-role.kubernetes.io/worker: ""

- Specify which CPUs are for infra containers to perform cluster and operating system housekeeping duties.
- Specify which CPUs are for application containers to run workloads.
- Optional: Specify a node selector to apply the performance profile to specific nodes.

18.6. REDUCING NIC QUEUES USING THE PERFORMANCE ADDON OPERATOR

The Performance Addon Operator allows you to adjust the Network Interface Card (NIC) queue count for each network device by configuring the performance profile. Device network queues allows the distribution of packets among different physical queues and each queue gets a separate thread for packet processing.

In real-time or low latency systems, all the unnecessary interrupt request lines (IRQs) pinned to the isolated CPUs must be moved to reserved or housekeeping CPUs.

In deployments with applications that require system, OpenShift Container Platform networking or in mixed deployments with Data Plane Development Kit (DPDK) workloads, multiple queues are needed to achieve good throughput and the number of NIC queues should be adjusted or remain unchanged. For example, to achieve low latency the number of NIC queues for DPDK based workloads should be reduced to just the number of reserved or housekeeping CPUs.

Too many queues are created by default for each CPU and these do not fit into the interrupt tables for housekeeping CPUs when tuning for low latency. Reducing the number of queues makes proper tuning possible. Smaller number of queues means a smaller number of interrupts that then fit in the IRQ table.

18.6.1. Adjusting the NIC queues with the performance profile

The performance profile lets you adjust the queue count for each network device.

Supported network devices:

- Non-virtual network devices
- Network devices that support multiple queues (channels)

Unsupported network devices:

- Pure software network interfaces
- Block devices

Intel DPDK virtual functions

Prerequisites

- Access to the cluster as a user with the cluster-admin role.
- Install the OpenShift CLI (oc).

Procedure

- 1. Log in to the OpenShift Container Platform cluster running the Performance Addon Operator as a user with **cluster-admin** privileges.
- 2. Create and apply a performance profile appropriate for your hardware and topology. For guidance on creating a profile, see the "Creating a performance profile" section.
- 3. Edit this created performance profile:
 - \$ oc edit -f <your_profile_name>.yaml
- 4. Populate the **spec** field with the **net** object. The object list can contain two fields:
 - userLevelNetworking is a required field specified as a boolean flag. If
 userLevelNetworking is true, the queue count is set to the reserved CPU count for all
 supported devices. The default is false.
 - devices is an optional field specifying a list of devices that will have the queues set to the reserved CPU count. If the device list is empty, the configuration applies to all network devices. The configuration is as follows:
 - **interfaceName**: This field specifies the interface name, and it supports shell-style wildcards, which can be positive or negative.
 - Example wildcard syntax is as follows: <string> .*
 - Negative rules are prefixed with an exclamation mark. To apply the net queue changes to all devices other than the excluded list, use !<device>, for example, !eno1.
 - **vendorID**: The network device vendor ID represented as a 16-bit hexadecimal number with a **0x** prefix.
 - **deviceID**: The network device ID (model) represented as a 16-bit hexadecimal number with a **0x** prefix.



NOTE

When a **deviceID** is specified, the **vendorID** must also be defined. A device that matches all of the device identifiers specified in a device entry **interfaceName**, **vendorID**, or a pair of **vendorID** plus **deviceID** qualifies as a network device. This network device then has its net queues count set to the reserved CPU count.

When two or more devices are specified, the net queues count is set to any net device that matches one of them.

5. Set the queue count to the reserved CPU count for all devices by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,54-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

6. Set the queue count to the reserved CPU count for all devices matching any of the defined device identifiers by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 name: manual
spec:
 cpu:
  isolated: 3-51,54-103
  reserved: 0-2,52-54
  userLevelNetworking: true
  devices:
  - interfaceName: "eth0"
  - interfaceName: "eth1"
  - vendorID: "0x1af4"
  deviceID: "0x1000"
 nodeSelector:
  node-role.kubernetes.io/worker-cnf: ""
```

7. Set the queue count to the reserved CPU count for all devices starting with the interface name **eth** by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,54-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
devices:
- interfaceName: "eth*"
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

8. Set the queue count to the reserved CPU count for all devices with an interface named anything other than **eno1** by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,54-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
devices:
- interfaceName: "!eno1"
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

9. Set the queue count to the reserved CPU count for all devices that have an interface name **eth0**, **vendorID** of **0x1af4**, and **deviceID** of **0x1000** by using this example performance profile:

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: manual
spec:
cpu:
isolated: 3-51,54-103
reserved: 0-2,52-54
net:
userLevelNetworking: true
devices:
- interfaceName: "eth0"
vendorID: "0x1af4"
deviceID: "0x1000"
nodeSelector:
node-role.kubernetes.io/worker-cnf: ""
```

10. Apply the updated performance profile:

```
$ oc apply -f <your_profile_name>.yaml
```

Additional resources

• Creating a performance profile.

18.6.2. Verifying the queue status

In this section, a number of examples illustrate different performance profiles and how to verify the changes are applied.

Example 1

In this example, the net queue count is set to the reserved CPU count (2) for all supported devices.

The relevant section from the performance profile is:

```
apiVersion: performance.openshift.io/v2
metadata:
name: performance
spec:
kind: PerformanceProfile
spec:
cpu:
reserved: 0-1 #total = 2
Isolated: 2-8
net:
userLevelNetworking: true
...
```

• Display the status of the queues associated with a device using the following command:



NOTE

Run this command on the node where the performance profile was applied.

\$ ethtool -l <device>

• Verify the queue status before the profile is applied:

```
$ ethtool -l ens4
```

Example output

Channel parameters for ens4:
Pre-set maximums:
RX: 0
TX: 0
Other: 0
Combined: 4
Current hardware settings:
RX: 0
TX: 0
Other: 0
Combined: 4

• Verify the queue status after the profile is applied:

\$ ethtool -I ens4

Example output

Channel parameters for ens4:
Pre-set maximums:
RX: 0
TX: 0
Other: 0

Combined: 4

Current hardware settings:

RX: 0 TX: 0 Other: 0 Combined: 2 1

The combined channel shows that the total count of reserved CPUs for *all* supported devices is 2. This matches what is configured in the performance profile.

Example 2

In this example, the net queue count is set to the reserved CPU count (2) for *all* supported network devices with a specific **vendorID**.

The relevant section from the performance profile is:

```
apiVersion: performance.openshift.io/v2
metadata:
name: performance
spec:
kind: PerformanceProfile
spec:
cpu:
reserved: 0-1 #total = 2
Isolated: 2-8
net:
userLevelNetworking: true
devices:
- vendorID = 0x1af4
...
```

• Display the status of the queues associated with a device using the following command:



NOTE

Run this command on the node where the performance profile was applied.

\$ ethtool -l <device>

• Verify the queue status after the profile is applied:

\$ ethtool -l ens4

Example output

Channel parameters for ens4:

Pre-set maximums:

RX: 0 TX: 0 Other: 0 Combined: 4

Current hardware settings:

RX: 0 TX: 0 Other: 0 Combined: 2 1

The total count of reserved CPUs for all supported devices with **vendorID=0x1af4** is 2. For example, if there is another network device **ens2** with **vendorID=0x1af4** it will also have total net queues of 2. This matches what is configured in the performance profile.

Example 3

In this example, the net queue count is set to the reserved CPU count (2) for *all* supported network devices that match any of the defined device identifiers.

The command **udevadm info** provides a detailed report on a device. In this example the devices are:

```
# udevadm info -p /sys/class/net/ens4
...
E: ID_MODEL_ID=0x1000
E: ID_VENDOR_ID=0x1af4
E: INTERFACE=ens4
...

# udevadm info -p /sys/class/net/eth0
...
E: ID_MODEL_ID=0x1002
E: ID_VENDOR_ID=0x1001
E: INTERFACE=eth0
...
```

• Set the net queues to 2 for a device with **interfaceName** equal to **eth0** and any devices that have a **vendorID=0x1af4** with the following performance profile:

```
apiVersion: performance.openshift.io/v2
metadata:
name: performance
spec:
kind: PerformanceProfile
spec:
cpu:
reserved: 0-1 #total = 2
Isolated: 2-8
net:
userLevelNetworking: true
devices:
- interfaceName = eth0
- vendorID = 0x1af4
....
```

Verify the queue status after the profile is applied:

```
$ ethtool -l ens4
```

Example output

Channel parameters for ens4:

Pre-set maximums:

RX: 0 TX: 0 Other: 0 Combined: 4

Current hardware settings:

RX: 0 TX: 0 Other: 0 Combined: 2 1

The total count of reserved CPUs for all supported devices with **vendorID=0x1af4** is set to 2. For example, if there is another network device **ens2** with **vendorID=0x1af4**, it will also have the total net queues set to 2. Similarly, a device with **interfaceName** equal to **eth0** will have total net queues set to 2.

18.6.3. Logging associated with adjusting NIC queues

Log messages detailing the assigned devices are recorded in the respective Tuned daemon logs. The following messages might be recorded to the /var/log/tuned/tuned.log file:

- An **INFO** message is recorded detailing the successfully assigned devices:
 - INFO tuned.plugins.base: instance net_test (net): assigning devices ens1, ens2, ens3
- A **WARNING** message is recorded if none of the devices can be assigned:

WARNING tuned.plugins.base: instance net_test: no matching devices available

18.7. PERFORMING END-TO-END TESTS FOR PLATFORM VERIFICATION

The Cloud-native Network Functions (CNF) tests image is a containerized test suite that validates features required to run CNF payloads. You can use this image to validate a CNF-enabled OpenShift cluster where all the components required for running CNF workloads are installed.

The tests run by the image are split into three different phases:

- Simple cluster validation
- Setup
- End to end tests

The validation phase checks that all the features required to be tested are deployed correctly on the cluster.

Validations include:

Targeting a machine config pool that belong to the machines to be tested

- Enabling SCTP on the nodes
- Enabling xt_u32 kernel module via machine config
- Having the Performance Addon Operator installed
- Having the SR-IOV Operator installed
- Having the PTP Operator installed
- Enabling the contain-mount-namespace mode via machine config
- Using OVN-kubernetes as the cluster network provider

Latency tests, a part of the CNF-test container, also require the same validations. For more information about running a latency test, see the Running the latency tests section.

The tests need to perform an environment configuration every time they are executed. This involves items such as creating SR-IOV node policies, performance profiles, or PTP profiles. Allowing the tests to configure an already configured cluster might affect the functionality of the cluster. Also, changes to configuration items such as SR-IOV node policy might result in the environment being temporarily unavailable until the configuration change is processed.

18.7.1. Prerequisites

- The test entrypoint is /usr/bin/test-run.sh. It runs both a setup test set and the real conformance test suite. The minimum requirement is to provide it with a kubeconfig file and its related **\$KUBECONFIG** environment variable, mounted through a volume.
- The tests assumes that a given feature is already available on the cluster in the form of an Operator, flags enabled on the cluster, or machine configs.
- Some tests require a pre-existing machine config pool to append their changes to. This must be created on the cluster before running the tests.

The default worker pool is worker-cnf and can be created with the following manifest:

```
apiVersion: machineconfiguration.openshift.io/v1
kind: MachineConfigPool
metadata:
 name: worker-cnf
 labels:
  machineconfiguration.openshift.io/role: worker-cnf
spec:
 machineConfigSelector:
  matchExpressions:
   - {
      key: machineconfiguration.openshift.io/role,
      operator: In,
      values: [worker-cnf, worker],
 paused: false
 nodeSelector:
  matchLabels:
   node-role.kubernetes.io/worker-cnf: ""
```

You can use the **ROLE_WORKER_CNF** variable to override the worker pool name:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig -e ROLE_WORKER_CNF=custom-worker-pool registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh



NOTE

Currently, not all tests run selectively on the nodes belonging to the pool.

18.7.2. Running the tests

Assuming the **kubeconfig** file is in the current folder, the command for running the test suite is:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh

This allows your **kubeconfig** file to be consumed from inside the running container.

18.7.2.1. Running the latency tests

In OpenShift Container Platform 4.8, you can also run latency tests from the CNF-test container. The latency test allows you to set a latency limit so that you can determine performance, throughput, and latency.

The latency test runs the **oslat** tool, which is an open source program to detect OS level latency. For more information, see the Red Hat Knowledgebase solution How to measure OS and hardware latency on isolated CPUs?.

By default, the latency tests are disabled. To enable the latency test, you must add the **LATENCY_TEST_RUN** variable and set its value to **true**. For example, **LATENCY_TEST_RUN=true**.

Additionally, you can set the following environment variables for latency tests:

- **LATENCY_TEST_RUNTIME** Specifies the amount of time (in seconds) that the latency test must run.
- OSLAT_MAXIMUM_LATENCY Specifies the maximum latency (in microseconds) that is expected from all buckets during the oslat test run.

To perform the latency tests, run the following command:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig -e LATENCY_TEST_RUN=true -e LATENCY_TEST_RUNTIME=600 -e OSLAT_MAXIMUM_LATENCY=20 registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh



NOTE

You must run the latency test in discovery mode. For more information, see the Discovery mode section.

Excerpt of a sample result of a 10-second latency test using the following command:

[root@cnf12-installer ~]# podman run --rm -v \$KUBECONFIG:/kubeconfig:Z -e

PERF_TEST_PROFILE=worker-cnf-2 -e KUBECONFIG=/kubeconfig -e LATENCY_TEST_RUN=true -e LATENCY_TEST_RUNTIME=10 -e OSLAT_MAXIMUM_LATENCY=20 -e DISCOVERY_MODE=true registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh -ginkgo.focus="Latency" running /0_config.test -ginkgo.focus=Latency

Example output

I1106 15:09:08.087085 7 request.go:621] Throttling request took 1.037172581s, request: GET:https://api.cnf12.kni.lab.eng.bos.redhat.com:6443/apis/autoscaling.openshift.io/v1?timeout=32s Running Suite: Performance Addon Operator configuration

Random Seed: 1604675347

Will run 0 of 1 specs

JUnit report was created: /unit_report_performance_config.xml

Ran 0 of 1 Specs in 0.000 seconds

SUCCESS! -- 0 Passed | 0 Failed | 0 Pending | 1 Skipped

PASS

running /4 latency.test -ginkgo.focus=Latency

I1106 15:09:10.735795 23 request.go:621] Throttling request took 1.037276624s, request: GET:https://api.cnf12.kni.lab.eng.bos.redhat.com:6443/apis/certificates.k8s.io/v1?timeout=32s Running Suite: Performance Addon Operator latency e2e tests

Random Seed: 1604675349

Will run 1 of 1 specs

I1106 15:10:06.401180 23 nodes.go:86] found mcd machine-config-daemon-r78qc for node cnfdd8.clus2.t5g.lab.eng.bos.redhat.com

I1106 15:10:06.738120 23 utils.go:23] run command 'oc [exec -i -n openshift-machine-configoperator -c machine-config-daemon --request-timeout 30 machine-config-daemon-r78qc -- cat /rootfs/var/log/oslat.log]' (err=<nil>):

stdout= Version: v0.1.7

Total runtime: 10 seconds
Thread priority: SCHED FIFO:1

CPU list:

3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,19,20,21,22,23,24,25,26,27,28,29,30,31,32,33,34,35,36,37,3

8,39,40,41,42,43,44,45,46,47,48,49,50

CPU for main thread: 2

Workload: no

Workload mem: 0 (KiB) Preheat cores: 48

Pre-heat for 1 seconds...

Test starts...
Test completed.

Core: 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50

18.7.3. Image parameters

Depending on the requirements, the tests can use different images. There are two images used by the tests that can be changed using the following environment variables:

- CNF_TESTS_IMAGE
- DPDK_TESTS_IMAGE

For example, to change the CNF_TESTS_IMAGE with a custom registry run the following command:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig -e CNF_TESTS_IMAGE="custom-cnf-tests-image:latests" registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh

18.7.3.1. Ginkgo parameters

The test suite is built upon the ginkgo BDD framework. This means that it accepts parameters for filtering or skipping tests.

You can use the **-ginkgo.focus** parameter to filter a set of tests:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh -ginkgo.focus="performance|sctp"

You can run only the latency test using the **-ginkgo.focus** parameter.

To run only the latency test, you must provide the **-ginkgo.focus** parameter and the **PERF_TEST_PROFILE** environment variable that contains the name of the performance profile that needs to be tested. For example:

\$ docker run --rm -v \$KUBECONFIG:/kubeconfig -e KUBECONFIG=/kubeconfig -e LATENCY_TEST_RUN=true -e LATENCY_TEST_RUNTIME=600 -e OSLAT_MAXIMUM_LATENCY=20 -e PERF_TEST_PROFILE=<performance_profile_name> registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh -ginkgo.focus="\[performance\]\ [config\]|\[performance\]\ Latency\ Test"



NOTE

There is a particular test that requires both SR-IOV and SCTP. Given the selective nature of the **focus** parameter, this test is triggered by only placing the **sriov** matcher. If the tests are executed against a cluster where SR-IOV is installed but SCTP is not, adding the **-ginkgo.skip=SCTP** parameter causes the tests to skip SCTP testing.

18.7.3.2. Available features

The set of available features to filter are:

performance

- sriov
- ptp
- sctp
- xt_u32
- dpdk
- container-mount-namespace

18.7.4. Dry run

Use this command to run in dry-run mode. This is useful for checking what is in the test suite and provides output for all of the tests the image would run.

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh -ginkgo.dryRun -ginkgo.v

18.7.5. Disconnected mode

The CNF tests image support running tests in a disconnected cluster, meaning a cluster that is not able to reach outer registries. This is done in two steps:

- 1. Performing the mirroring.
- 2. Instructing the tests to consume the images from a custom registry.

18.7.5.1. Mirroring the images to a custom registry accessible from the cluster

A **mirror** executable is shipped in the image to provide the input required by **oc** to mirror the images needed to run the tests to a local registry.

Run this command from an intermediate machine that has access both to the cluster and to registry.redhat.io over the internet:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/mirror -registry my.local.registry:5000/ | oc image mirror -f -

Then, follow the instructions in the following section about overriding the registry used to fetch the images.

18.7.5.2. Instruct the tests to consume those images from a custom registry

This is done by setting the **IMAGE_REGISTRY** environment variable:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig -e IMAGE_REGISTRY="my.local.registry:5000/" -e CNF_TESTS_IMAGE="custom-cnf-tests-image:latests" registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh

18.7.5.3. Mirroring to the cluster internal registry

OpenShift Container Platform provides a built-in container image registry, which runs as a standard workload on the cluster.

Procedure

1. Gain external access to the registry by exposing it with a route:

\$ oc patch configs.imageregistry.operator.openshift.io/cluster --patch '{"spec": {"defaultRoute":true}}' --type=merge

2. Fetch the registry endpoint:

REGISTRY=\$(oc get route default-route -n openshift-image-registry --template='{{ .spec.host }}')

- 3. Create a namespace for exposing the images:
 - \$ oc create ns cnftests
- 4. Make that image stream available to all the namespaces used for tests. This is required to allow the tests namespaces to fetch the images from the **cnftests** image stream.
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:sctptest:default -- namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:cnf-features-testing:default --namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:performance-addon-operators-testing:default --namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:dpdk-testing:default --namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:sriov-conformance-testing:default --namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:xt-u32-testing:default --namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:vrf-testing:default -- namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:gatekeeper-testing:default --namespace=cnftests
 - \$ oc policy add-role-to-user system:image-puller system:serviceaccount:ovs-qostesting:default --namespace=cnftests
- 5. Retrieve the docker secret name and auth token:

SECRET=\$(oc -n cnftests get secret | grep builder-docker | awk {'print \$1'}
TOKEN=\$(oc -n cnftests get secret \$SECRET -o jsonpath="{.data['\.dockercfg']}" | base64 -decode | jq '.["image-registry.openshift-image-registry.svc:5000"].auth')

6. Write a **dockerauth.json** similar to this:

```
echo "{\"auths\": { \"$REGISTRY\": { \"auth\": $TOKEN } }}" > dockerauth.json
```

7. Do the mirroring:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/mirror -registry \$REGISTRY/cnftests oc image mirror --insecure=true -a=\$(pwd)/dockerauth.json -f -

8. Run the tests:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig -e IMAGE_REGISTRY=image-registry.openshift-image-registry.svc:5000/cnftests cnf-tests-local:latest /usr/bin/test-run.sh

18.7.5.4. Mirroring a different set of images

Procedure

1. The **mirror** command tries to mirror the u/s images by default. This can be overridden by passing a file with the following format to the image:

2. Pass it to the **mirror** command, for example saving it locally as **images.json**. With the following command, the local path is mounted in /**kubeconfig** inside the container and that can be passed to the mirror command.

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/mirror --registry "my.local.registry:5000/" --images "/kubeconfig/images.json" | oc image mirror -f -

18.7.6. Discovery mode

Discovery mode allows you to validate the functionality of a cluster without altering its configuration. Existing environment configurations are used for the tests. The tests attempt to find the configuration items needed and use those items to execute the tests. If resources needed to run a specific test are

not found, the test is skipped, providing an appropriate message to the user. After the tests are finished, no cleanup of the pre-configured configuration items is done, and the test environment can be immediately used for another test run.

Some configuration items are still created by the tests. These are specific items needed for a test to run; for example, a SR-IOV Network. These configuration items are created in custom namespaces and are cleaned up after the tests are executed.

An additional bonus is a reduction in test run times. As the configuration items are already there, no time is needed for environment configuration and stabilization.

To enable discovery mode, the tests must be instructed by setting the **DISCOVERY_MODE** environment variable as follows:

 $\label{lem:config} $$ docker run -v (pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig -e DISCOVERY_MODE=true registry.redhat.io/openshift-kni/cnf-tests /usr/bin/test-run.sh$

18.7.6.1. Required environment configuration prerequisites

SR-IOV tests

Most SR-IOV tests require the following resources:

- SriovNetworkNodePolicy.
- At least one with the resource specified by **SriovNetworkNodePolicy** being allocatable; a resource count of at least 5 is considered sufficient.

Some tests have additional requirements:

- An unused device on the node with available policy resource, with link state **DOWN** and not a bridge slave.
- A **SriovNetworkNodePolicy** with a MTU value of **9000**.

DPDK tests

The DPDK related tests require:

- A performance profile.
- A SR-IOV policy.
- A node with resources available for the SR-IOV policy and available with the **PerformanceProfile** node selector.

PTP tests

- A slave PtpConfig (ptp4lOpts="-s",phc2sysOpts="-a -r").
- A node with a label matching the slave **PtpConfig**.

SCTP tests

SriovNetworkNodePolicy.

A node matching both the SriovNetworkNodePolicy and a MachineConfig that enables
 SCTP

XT_U32 tests

• A node with a machine config that enables XT_U32.

Performance Operator tests

Various tests have different requirements. Some of them are:

- A performance profile.
- A performance profile having **profile.Spec.CPU.Isolated = 1**.
- A performance profile having profile.Spec.RealTimeKernel.Enabled == true.
- A node with no huge pages usage.

Container-mount-namespace tests

• A node with a machine config which enables **container-mount-namespace** mode

18.7.6.2. Limiting the nodes used during tests

The nodes on which the tests are executed can be limited by specifying a **NODES_SELECTOR** environment variable. Any resources created by the test are then limited to the specified nodes.

\$ docker run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig -e NODES_SELECTOR=node-role.kubernetes.io/worker-cnf registry.redhat.io/openshift-kni/cnf-tests/usr/bin/test-run.sh

18.7.6.3. Using a single performance profile

The resources needed by the DPDK tests are higher than those required by the performance test suite. To make the execution faster, the performance profile used by tests can be overridden using one that also serves the DPDK test suite.

To do this, a profile like the following one can be mounted inside the container, and the performance tests can be instructed to deploy it.

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
name: performance
spec:
cpu:
isolated: "4-15"
reserved: "0-3"
hugepages:
defaultHugepagesSize: "1G"
pages:
- size: "1G"
count: 16
node: 0
```

realTimeKernel: enabled: true nodeSelector:

node-role.kubernetes.io/worker-cnf: ""



NOTE

When you configure reserved and isolated CPUs, the infra containers in pods use the reserved CPUs and the application containers use the isolated CPUs.

To override the performance profile used, the manifest must be mounted inside the container and the tests must be instructed by setting the **PERFORMANCE_PROFILE_MANIFEST_OVERRIDE** parameter as follows:

\$ docker run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig -e PERFORMANCE_PROFILE_MANIFEST_OVERRIDE=/kubeconfig/manifest.yaml registry.redhat.io/openshift-kni/cnf-tests /usr/bin/test-run.sh

18.7.6.4. Disabling the performance profile cleanup

When not running in discovery mode, the suite cleans up all the created artifacts and configurations. This includes the performance profile.

When deleting the performance profile, the machine config pool is modified and nodes are rebooted. After a new iteration, a new profile is created. This causes long test cycles between runs.

To speed up this process, set **CLEAN_PERFORMANCE_PROFILE="false"** to instruct the tests not to clean the performance profile. In this way, the next iteration will not need to create it and wait for it to be applied.

\$ docker run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig -e CLEAN_PERFORMANCE_PROFILE="false" registry.redhat.io/openshift-kni/cnf-tests /usr/bin/test-run.sh

18.7.7. Running in a single node cluster

Running tests on a single node cluster causes the following limitations to be imposed:

- Longer timeouts for certain tests, including SR-IOV and SCTP tests
- Tests requiring master and worker nodes are skipped

Longer timeouts concern SR-IOV and SCTP tests. Reconfiguration requiring node reboots cause a reboot of the entire environment, including the OpenShift control plane, and therefore takes longer to complete. All PTP tests requiring a master and worker node are skipped. No additional configuration is needed because the tests check for the number of nodes at startup and adjust test behavior accordingly.

PTP tests can run in Discovery mode. The tests look for a PTP master configured outside of the cluster.

For more information, see the Discovery mode section.

To enable Discovery mode, the tests must be instructed by setting the **DISCOVERY_MODE** environment variable as follows:

\$ docker run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig -e DISCOVERY_MODE=true registry.redhat.io/openshift-kni/cnf-tests /usr/bin/test-run.sh

Required parameters

- **ROLE_WORKER_CNF=master** Required because master is the only machine pool to which the node will belong.
- XT_U32TEST_HAS_NON_CNF_WORKERS=false Required to instruct the xt_u32 negative test to skip because there are only nodes where the module is loaded.
- SCTPTEST_HAS_NON_CNF_WORKERS=false Required to instruct the SCTP negative test
 to skip because there are only nodes where the module is loaded.

18.7.8. Troubleshooting

The cluster must be reached from within the container. You can verify this by running:

\$ docker run -v \$(pwd)/:/kubeconfig -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift-kni/cnf-tests oc get nodes

If this does not work, it could be caused by spanning across DNS, MTU size, or firewall issues.

18.7.9. Test reports

CNF end-to-end tests produce two outputs: a JUnit test output and a test failure report.

18.7.9.1. JUnit test output

A JUnit-compliant XML is produced by passing the **--junit** parameter together with the path where the report is dumped:

\$ docker run -v \$(pwd)/:/kubeconfig -v \$(pwd)/junitdest:/path/to/junit -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh --junit /path/to/junit

18.7.9.2. Test failure report

A report with information about the cluster state and resources for troubleshooting can be produced by passing the **--report** parameter with the path where the report is dumped:

\$ docker run -v \$(pwd)/:/kubeconfig -v \$(pwd)/reportdest:/path/to/report -e KUBECONFIG=/kubeconfig/kubeconfig registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh --report /path/to/report

18.7.9.3. A note on podman

When executing podman as non root and non privileged, mounting paths can fail with "permission denied" errors. To make it work, append :Z to the volumes creation; for example, -v \$(pwd)/:/kubeconfig:Z to allow podman to do the proper SELinux relabeling.

18.7.9.4. Running on OpenShift Container Platform 4.4

With the exception of the following, the CNF end-to-end tests are compatible with OpenShift Container Platform 4.4:

[test_id:28466][crit:high][vendor:cnf-qe@redhat.com][level:acceptance] Should contain configuration injected through openshift-node-performance profile [test_id:28467][crit:high][vendor:cnf-qe@redhat.com][level:acceptance] Should contain configuration injected through the openshift-node-performance profile

You can skip these tests by adding the -ginkgo.skip "28466|28467" parameter.

18.7.9.5. Using a single performance profile

The DPDK tests require more resources than what is required by the performance test suite. To make the execution faster, you can override the performance profile used by the tests using a profile that also serves the DPDK test suite.

To do this, use a profile like the following one that can be mounted inside the container, and the performance tests can be instructed to deploy it.

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: performance spec: cpu: isolated: "5-15" reserved: "0-4" hugepages: defaultHugepagesSize: "1G" pages: - size: "1G" count: 16 node: 0 realTimeKernel: enabled: true numa: topologyPolicy: "best-effort" nodeSelector: node-role.kubernetes.io/worker-cnf: ""



NOTE

When you configure reserved and isolated CPUs, the infra containers in pods use the reserved CPUs and the application containers use the isolated CPUs.

To override the performance profile, the manifest must be mounted inside the container and the tests must be instructed by setting the **PERFORMANCE PROFILE MANIFEST OVERRIDE**:

\$ docker run -v \$(pwd)/:/kubeconfig:Z -e KUBECONFIG=/kubeconfig/kubeconfig -e PERFORMANCE_PROFILE_MANIFEST_OVERRIDE=/kubeconfig/manifest.yaml registry.redhat.io/openshift4/cnf-tests-rhel8:v4.8 /usr/bin/test-run.sh

18.7.10. Impacts on the cluster

Depending on the feature, running the test suite could cause different impacts on the cluster. In general, only the SCTP tests do not change the cluster configuration. All of the other features have various impacts on the configuration.

18.7.10.1. SCTP

SCTP tests just run different pods on different nodes to check connectivity. The impacts on the cluster are related to running simple pods on two nodes.

18.7.10.2. XT_U32

XT_U32 tests run pods on different nodes to check iptables rule that utilize xt_u32. The impacts on the cluster are related to running simple pods on two nodes.

18.7.10.3. SR-IOV

SR-IOV tests require changes in the SR-IOV network configuration, where the tests create and destroy different types of configuration.

This might have an impact if existing SR-IOV network configurations are already installed on the cluster, because there may be conflicts depending on the priority of such configurations.

At the same time, the result of the tests might be affected by existing configurations.

18.7.10.4. PTP

PTP tests apply a PTP configuration to a set of nodes of the cluster. As with SR-IOV, this might conflict with any existing PTP configuration already in place, with unpredictable results.

18.7.10.5. Performance

Performance tests apply a performance profile to the cluster. The effect of this is changes in the node configuration, reserving CPUs, allocating memory huge pages, and setting the kernel packages to be realtime. If an existing profile named **performance** is already available on the cluster, the tests do not deploy it.

18.7.10.6. DPDK

DPDK relies on both performance and SR-IOV features, so the test suite configures both a performance profile and SR-IOV networks, so the impacts are the same as those described in SR-IOV testing and performance testing.

18.7.10.7. Container-mount-namespace

The validation test for **container-mount-namespace** mode only checks that the appropriate **MachineConfig** objects are present and active, and has no additional impact on the node.

18.7.10.8. Cleaning up

After running the test suite, all the dangling resources are cleaned up.

18.8. DEBUGGING LOW LATENCY CNF TUNING STATUS

The **PerformanceProfile** custom resource (CR) contains status fields for reporting tuning status and debugging latency degradation issues. These fields report on conditions that describe the state of the operator's reconciliation functionality.

A typical issue can arise when the status of machine config pools that are attached to the performance profile are in a degraded state, causing the **PerformanceProfile** status to degrade. In this case, the machine config pool issues a failure message.

The Performance Addon Operator contains the **performanceProfile.spec.status.Conditions** status field:

Status:

Conditions:

Last Heartbeat Time: 2020-06-02T10:01:24Z Last Transition Time: 2020-06-02T10:01:24Z

Status: True Type: Available

Last Heartbeat Time: 2020-06-02T10:01:24Z Last Transition Time: 2020-06-02T10:01:24Z

Status: True

Type: Upgradeable

Last Heartbeat Time: 2020-06-02T10:01:24Z Last Transition Time: 2020-06-02T10:01:24Z

Status: False Type: Progressing

Last Heartbeat Time: 2020-06-02T10:01:24Z Last Transition Time: 2020-06-02T10:01:24Z

Status: False Type: Degraded

The **Status** field contains **Conditions** that specify **Type** values that indicate the status of the performance profile:

Available

All machine configs and Tuned profiles have been created successfully and are available for cluster components are responsible to process them (NTO, MCO, Kubelet).

Upgradeable

Indicates whether the resources maintained by the Operator are in a state that is safe to upgrade.

Progressing

Indicates that the deployment process from the performance profile has started.

Degraded

Indicates an error if:

- Validation of the performance profile has failed.
- Creation of all relevant components did not complete successfully.

Each of these types contain the following fields:

Status

The state for the specific type (**true** or **false**).

Timestamp

The transaction timestamp.

Reason string

The machine readable reason.

Message string

The human readable reason describing the state and error details, if any.

18.8.1. Machine config pools

A performance profile and its created products are applied to a node according to an associated machine config pool (MCP). The MCP holds valuable information about the progress of applying the machine configurations created by performance addons that encompass kernel args, kube config, huge pages allocation, and deployment of rt-kernel. The performance addons controller monitors changes in the MCP and updates the performance profile status accordingly.

The only conditions returned by the MCP to the performance profile status is when the MCP is **Degraded**, which leads to **performaceProfile.status.condition.Degraded = true**.

Example

The following example is for a performance profile with an associated machine config pool (**worker-cnf**) that was created for it:

1. The associated machine config pool is in a degraded state:

oc get mcp

Example output

```
NAME
                                         UPDATED UPDATING DEGRADED
         CONFIG
MACHINECOUNT READYMACHINECOUNT UPDATEDMACHINECOUNT
DEGRADEDMACHINECOUNT AGE
        rendered-master-2ee57a93fa6c9181b546ca46e1571d2d
                                                         True
                                                                False
master
False
                         3
                                                 2d21h
       rendered-worker-d6b2bdc07d9f5a59a6b68950acf25e5f
worker
                                                        True
                                                               False
False
               2
                         2
                                                 2d21h
worker-cnf rendered-worker-cnf-6c838641b8a08fff08dbd8b02fb63f7c False
                                                                True
True
                                                 2d20h
```

2. The **describe** section of the MCP shows the reason:

oc describe mcp worker-cnf

Example output

Message: Node node-worker-cnf is reporting: "prepping update: machineconfig.machineconfiguration.openshift.io \"rendered-worker-cnf-40b9996919c08e335f3ff230ce1d170\" not found"

Reason: 1 nodes are reporting degraded status on sync

3. The degraded state should also appear under the performance profile **status** field marked as **degraded = true**:

oc describe performanceprofiles performance

Example output

Message: Machine config pool worker-cnf Degraded Reason: 1 nodes are reporting degraded status on sync.

Machine config pool worker-cnf Degraded Message: Node yquinn-q8s5v-w-b-z5lqn.c.openshift-gce-devel.internal is

reporting: "prepping update: machineconfig.machineconfiguration.openshift.io \"rendered-worker-cnf-40b9996919c08e335f3ff230ce1d170\" not found". Reason:

MCPDegraded Status: True Type: Degraded

18.9. COLLECTING LOW LATENCY TUNING DEBUGGING DATA FOR RED HAT SUPPORT

When opening a support case, it is helpful to provide debugging information about your cluster to Red Hat Support.

The **must-gather** tool enables you to collect diagnostic information about your OpenShift Container Platform cluster, including node tuning, NUMA topology, and other information needed to debug issues with low latency setup.

For prompt support, supply diagnostic information for both OpenShift Container Platform and low latency tuning.

18.9.1. About the must-gather tool

The **oc adm must-gather** CLI command collects the information from your cluster that is most likely needed for debugging issues, such as:

- Resource definitions
- Audit logs
- Service logs

You can specify one or more images when you run the command by including the **--image** argument. When you specify an image, the tool collects data related to that feature or product. When you run **oc adm must-gather**, a new pod is created on the cluster. The data is collected on that pod and saved in a new directory that starts with **must-gather.local**. This directory is created in your current working directory.

18.9.2. About collecting low latency tuning data

Use the **oc adm must-gather** CLI command to collect information about your cluster, including features and objects associated with low latency tuning, including:

- The Performance Addon Operator namespaces and child objects.
- MachineConfigPool and associated MachineConfig objects.
- The Node Tuning Operator and associated Tuned objects.

- Linux Kernel command line options.
- CPU and NUMA topology
- Basic PCI device information and NUMA locality.

To collect container-native virtualization data with **must-gather**, you must specify the container-native virtualization image:

--image=registry.redhat.io/openshift4/performance-addon-operator-must-gather-rhel8.

18.9.3. Gathering data about specific features

You can gather debugging information about specific features by using the **oc adm must-gather** CLI command with the **--image** or **--image-stream** argument. The **must-gather** tool supports multiple images, so you can gather data about more than one feature by running a single command.



NOTE

To collect the default **must-gather** data in addition to specific feature data, add the **-- image-stream=openshift/must-gather** argument.

Prerequisites

- Access to the cluster as a user with the **cluster-admin** role.
- The OpenShift Container Platform CLI (oc) installed.

Procedure

- 1. Navigate to the directory where you want to store the **must-gather** data.
- 2. Run the **oc adm must-gather** command with one or more **--image** or **--image-stream** arguments. For example, the following command gathers both the default cluster data and information specific to container-native virtualization:

\$ oc adm must-gather \

- --image-stream=openshift/must-gather \ 1
- --image=registry.redhat.io/openshift4/performance-addon-operator-must-gather-rhel8 (2)
- The default OpenShift Container Platform **must-gather** image.
- The **must-gather** image for low latency tuning diagnostics.
- 3. Create a compressed file from the **must-gather** directory that was created in your working directory. For example, on a computer that uses a Linux operating system, run the following command:
 - \$ tar cvaf must-gather.tar.gz must-gather.local.5421342344627712289/
 - Replace **must-gather-local.5421342344627712289**/ with the actual directory name.

4. Attach the compressed file to your support case on the Red Hat Customer Portal.

Additional resources

- For more information about MachineConfig and KubeletConfig, see Managing nodes.
- For more information about the Node Tuning Operator, see Using the Node Tuning Operator.
- For more information about the PerformanceProfile, see Configuring huge pages.
- For more information about consuming huge pages from your containers, see How huge pages are consumed by apps.

CHAPTER 19. CREATING A PERFORMANCE PROFILE

Learn about the Performance Profile Creator (PPC) and how you can use it to create a performance profile.

19.1. ABOUT THE PERFORMANCE PROFILE CREATOR

The Performance Profile Creator (PPC) is a command-line tool, delivered with the Performance Addon Operator, used to create the performance profile. The tool consumes **must-gather** data from the cluster and several user-supplied profile arguments. The PPC generates a performance profile that is appropriate for your hardware and topology.

The tool is run by one of the following methods:

- Invoking podman
- Calling a wrapper script

19.1.1. Gathering data about your cluster using must-gather

The Performance Profile Creator (PPC) tool requires **must-gather** data. As a cluster administrator, run **must-gather** to capture information about your cluster.

Prerequisites

- Access to the cluster as a user with the **cluster-admin** role.
- Access to the Performance Addon Operator image.
- The OpenShift CLI (oc) installed.

Procedure

- 1. Navigate to the directory where you want to store the **must-gather** data.
- 2. Run **must-gather** on your cluster:

\$ oc adm must-gather --image=<PAO_image> --dest-dir=<dir>



NOTE

must-gather must be run with the **performance-addon-operator-must-gather** image. The output can optionally be compressed. Compressed output is required if you are running the Performance Profile Creator wrapper script.

Example

\$ oc adm must-gather --image=quay.io/openshift-kni/performance-addon-operator-must-gather:4.8-snapshot --dest-dir=must-gather

3. Create a compressed file from the **must-gather** directory:

\$ tar cvaf must-gather.tar.gz must-gather/

19.1.2. Running the Performance Profile Creator using podman

As a cluster administrator, you can run **podman** and the Performance Profile Creator to create a performance profile.

Prerequisites

- Access to the cluster as a user with the **cluster-admin** role.
- A cluster installed on bare metal hardware.
- A node with **podman** and OpenShift CLI (**oc**) installed.

Procedure

1. Check the machine config pool:

\$ oc get mcp

Example output

NAME UPDATED UPDATING DEGRADED **CONFIG** MACHINECOUNT READYMACHINECOUNT UPDATEDMACHINECOUNT DEGRADEDMACHINECOUNT AGE rendered-master-acd1358917e9f98cbdb599aea622d78b master True False False 3 worker-cnf rendered-worker-cnf-1d871ac76e1951d32b2fe92369879826 False True False 1 1 22h

2. Optional: Display help for the PPC tool:

\$ podman run --entrypoint performance-profile-creator quay.io/openshift-kni/performanceaddon-operator:4.8-snapshot -h

Example output

A tool that automates creation of Performance Profiles

Usage:

performance-profile-creator [flags]

Flags:

--disable-ht Disable Hyperthreading

-h, --help help for performance-profile-creator

--info string Show cluster information; requires --must-gather-dir-path,

ignore the other arguments. [Valid values: log, json] (default "log")

--mcp-name string MCP name corresponding to the target machines

(required)

Must gather directory path (default "must-gather") --must-gather-dir-path string

--power-consumption-mode string The power consumption mode. [Valid values: default, low-latency, ultra-low-latency] (default "default")

--profile-name string Name of the performance profile to be created (default "performance")

--reserved-cpu-count int Number of reserved CPUs (required)

--rt-kernel Enable Real Time Kernel (required)

- --split-reserved-cpus-across-numa Split the Reserved CPUs across NUMA nodes
- --topology-manager-policy string Kubelet Topology Manager Policy of the performance profile to be created. [Valid values: single-numa-node, best-effort, restricted] (default "restricted")
 - --user-level-networking Run with User level Networking(DPDK) enabled

3. Run the Performance Profile Creator tool in discovery mode:



NOTE

Discovery mode inspects your cluster using the output from **must-gather**. The output produced includes information on:

- The NUMA cell partitioning with the allocated CPU ids
- Whether hyperthreading is enabled

Using this information you can set appropriate values for some of the arguments supplied to the Performance Profile Creator tool.

\$ podman run --entrypoint performance-profile-creator -v /must-gather:/must-gather:z quay.io/openshift-kni/performance-addon-operator:4.8-snapshot --info log --must-gather-dir-path /must-gather



NOTE

This command uses the performance profile creator as a new entry point to **podman**. It maps the **must-gather** data for the host into the container image and invokes the required user-supplied profile arguments to produce the **my-performance-profile.yaml** file.

The **-v** option can be the path to either:

- The must-gather output directory
- An existing directory containing the **must-gather** decompressed tarball

The **info** option requires a value which specifies the output format. Possible values are log and JSON. The JSON format is reserved for debugging.

4. Run podman:

\$ podman run --entrypoint performance-profile-creator -v /must-gather:/must-gather:z quay.io/openshift-kni/performance-addon-operator:4.8-snapshot --mcp-name=worker-cnf -- reserved-cpu-count=20 --rt-kernel=true --split-reserved-cpus-across-numa=false --topology-manager-policy=single-numa-node --must-gather-dir-path /must-gather --power-consumption-mode=ultra-low-latency > my-performance-profile.yaml



NOTE

The Performance Profile Creator arguments are shown in the Performance Profile Creator arguments table. The following arguments are required:

- reserved-cpu-count
- mcp-name
- rt-kernel

The **mcp-name** argument in this example is set to **worker-cnf** based on the output of the command **oc get mcp**. For Single Node OpenShift (SNO) use **--mcp-name=master**.

5. Review the created YAML file:

\$ cat my-performance-profile.yaml

Example output

```
apiVersion: performance.openshift.io/v2
kind: PerformanceProfile
metadata:
 name: performance
spec:
 additionalKernelArgs:
 - nmi watchdog=0
 - audit=0
 - mce=off
 - processor.max_cstate=1
 - intel_idle.max_cstate=0
 - idle=poll
 cpu:
  isolated: 1,3,5,7,9,11,13,15,17,19-39,41,43,45,47,49,51,53,55,57,59-79
  reserved: 0,2,4,6,8,10,12,14,16,18,40,42,44,46,48,50,52,54,56,58
 nodeSelector:
  node-role.kubernetes.io/worker-cnf: ""
 numa:
  topologyPolicy: single-numa-node
 realTimeKernel:
  enabled: true
```

6. Apply the generated profile:

\$ oc apply -f my-performance-profile.yaml

19.1.2.1. How to run podman to create a performance profile

The following example illustrates how to run **podman** to create a performance profile with 20 reserved CPUs that are to be split across the NUMA nodes.

Node hardware configuration:

- 80 CPUs
- Hyperthreading enabled
- Two NUMA nodes
- Even numbered CPUs run on NUMA node 0 and odd numbered CPUs run on NUMA node 1

Run **podman** to create the performance profile:

\$ podman run --entrypoint performance-profile-creator -v /must-gather:/must-gather:z quay.io/openshift-kni/performance-addon-operator:4.8-snapshot --mcp-name=worker-cnf --reserved-cpu-count=20 --rt-kernel=true --split-reserved-cpus-across-numa=true --must-gather-dir-path /must-gather > my-performance-profile.yaml

The created profile is described in the following YAML:

```
apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: performance spec: cpu: isolated: 10-39,50-79 reserved: 0-9,40-49 nodeSelector: node-role.kubernetes.io/worker-cnf: "" numa: topologyPolicy: restricted realTimeKernel: enabled: true
```



NOTE

In this case, 10 CPUs are reserved on NUMA node 0 and 10 are reserved on NUMA node 1.

19.1.3. Running the Performance Profile Creator wrapper script

The performance profile wrapper script simplifies the running of the Performance Profile Creator (PPC) tool. It hides the complexities associated with running **podman** and specifying the mapping directories and it enables the creation of the performance profile.

Prerequisites

- Access to the Performance Addon Operator image.
- Access to the **must-gather** tarball.

Procedure

1. Create a file on your local machine named, for example, run-perf-profile-creator.sh:

\$ vi run-perf-profile-creator.sh

2. Paste the following code into the file:

```
#!/bin/bash
readonly CONTAINER RUNTIME=${CONTAINER RUNTIME:-podman}
readonly CURRENT SCRIPT=$(basename "$0")
readonly CMD="${CONTAINER RUNTIME} run --entrypoint performance-profile-creator"
readonly IMG EXISTS CMD="${CONTAINER RUNTIME} image exists"
readonly IMG_PULL_CMD="${CONTAINER_RUNTIME} image pull"
readonly MUST GATHER VOL="/must-gather"
PAO_IMG="quay.io/openshift-kni/performance-addon-operator:4.8-snapshot"
MG TARBALL=""
DATA_DIR=""
usage() {
 print "Wrapper usage:"
 print " ${CURRENT_SCRIPT} [-h] [-p image][-t path] -- [performance-profile-creator flags]"
 print ""
 print "Options:"
 print " -h
                   help for ${CURRENT SCRIPT}"
                  Performance Addon Operator image"
 print " -p
 print " -t
                  path to a must-gather tarball"
 ${IMG_EXISTS_CMD} "${PAO_IMG}" && ${CMD} "${PAO_IMG}" -h
}
function cleanup {
 [-d "${DATA DIR}" ] && rm -rf "${DATA DIR}"
trap cleanup EXIT
exit error() {
 print "error: $*"
 usage
 exit 1
}
print() {
 echo "$*" >&2
}
check requirements() {
 ${IMG_EXISTS_CMD} "${PAO_IMG}" || ${IMG_PULL_CMD} "${PAO_IMG}" || \
   exit error "Performance Addon Operator image not found"
 [ -n "${MG_TARBALL}" ] || exit_error "Must-gather tarball file path is mandatory"
 [-f "${MG TARBALL}"]|| exit error "Must-gather tarball file not found"
 DATA_DIR=$(mktemp -d -t "${CURRENT_SCRIPT}XXXX") || exit_error "Cannot create the
data directory"
 tar -zxf "${MG_TARBALL}" --directory "${DATA_DIR}" || exit_error "Cannot decompress the
must-gather tarball"
 chmod a+rx "${DATA_DIR}"
 return 0
```

```
main() {
 while getopts ':hp:t:' OPT; do
  case "${OPT}" in
   h)
    usage
    exit 0
   p)
    PAO_IMG="${OPTARG}"
   t)
    MG_TARBALL="${OPTARG}"
   ?)
    exit_error "invalid argument: ${OPTARG}"
  esac
 done
 shift $((OPTIND - 1))
 check_requirements || exit 1
 ${CMD} -v "${DATA_DIR}:${MUST_GATHER_VOL}:z" "${PAO_IMG}" "$@" --must-gather-
dir-path "${MUST_GATHER_VOL}"
 echo "" 1>&2
main "$@"
```

- 3. Add execute permissions for everyone on this script:
 - \$ chmod a+x run-perf-profile-creator.sh
- 4. Optional: Display the **run-perf-profile-creator.sh** command usage:
 - \$./run-perf-profile-creator.sh -h

Expected output

```
Wrapper usage:
run-perf-profile-creator.sh [-h] [-p image][-t path] -- [performance-profile-creator flags]

Options:
-h help for run-perf-profile-creator.sh
-p Performance Addon Operator image 1
-t path to a must-gather tarball 2

A tool that automates creation of Performance Profiles

Usage:
performance-profile-creator [flags]
```

Flags:

--disable-ht Disable Hyperthreading

-h, --help help for performance-profile-creator

--info string Show cluster information; requires --must-gather-dir-path,

ignore the other arguments. [Valid values: log, json] (default "log")

--mcp-name string MCP name corresponding to the target machines (required)

--must-gather-dir-path string Must gather directory path (default "must-gather")

--power-consumption-mode string The power consumption mode. [Valid values: default, low-latency, ultra-low-latency] (default "default")

--profile-name string Name of the performance profile to be created (default "performance")

--reserved-cpu-count int Number of reserved CPUs (required)

--rt-kernel Enable Real Time Kernel (required)

--split-reserved-cpus-across-numa Split the Reserved CPUs across NUMA nodes

--topology-manager-policy string Kubelet Topology Manager Policy of the performance profile to be created. [Valid values: single-numa-node, best-effort, restricted] (default "restricted")

--user-level-networking Run with User level Networking(DPDK) enabled



NOTE

There two types of arguments:

- Wrapper arguments namely **-h**, **-p** and **-t**
- PPC arguments
- Optional: Specify the Performance Addon Operator image. If not set, the default upstream image is used: quay.io/openshift-kni/performance-addon-operator:4.8-snapshot.
- -t is a required wrapper script argument and specifies the path to a **must-gather** tarball.
- 5. Run the performance profile creator tool in discovery mode:



NOTE

Discovery mode inspects your cluster using the output from **must-gather**. The output produced includes information on:

- The NUMA cell partitioning with the allocated CPU IDs
- Whether hyperthreading is enabled

Using this information you can set appropriate values for some of the arguments supplied to the Performance Profile Creator tool.

\$./run-perf-profile-creator.sh -t /must-gather/must-gather.tar.gz -- --info=log



NOTE

The **info** option requires a value which specifies the output format. Possible values are log and JSON. The JSON format is reserved for debugging.

6. Check the machine config pool:

\$ oc get mcp

Example output

NAME CONFIG UPDATED UPDATING DEGRADED MACHINECOUNT READYMACHINECOUNT UPDATEDMACHINECOUNT DEGRADEDMACHINECOUNT AGE master rendered-master-acd1358917e9f98cbdb599aea622d78b True False False 3 3 0 22h worker-cnf rendered-worker-cnf-1d871ac76e1951d32b2fe92369879826 False True False 2 1 1 0 22h

7. Create a performance profile:

\$./run-perf-profile-creator.sh -t /must-gather/must-gather.tar.gz -- --mcp-name=worker-cnf -- reserved-cpu-count=2 --rt-kernel=true > my-performance-profile.yaml



NOTE

The Performance Profile Creator arguments are shown in the Performance Profile Creator arguments table. The following arguments are required:

- reserved-cpu-count
- mcp-name
- rt-kernel

The **mcp-name** argument in this example is set to **worker-cnf** based on the output of the command **oc get mcp**. For Single Node OpenShift (SNO) use **--mcp-name=master**.

8. Review the created YAML file:

\$ cat my-performance-profile.yaml

Example output

apiVersion: performance.openshift.io/v2 kind: PerformanceProfile metadata: name: performance spec: cpu: isolated: 1-39,41-79 reserved: 0,40 nodeSelector: node-role.kubernetes.io/worker-cnf: "" numa:

topologyPolicy: restricted

realTimeKernel: enabled: false

9. Apply the generated profile:

\$ oc apply -f my-performance-profile.yaml

19.1.4. Performance Profile Creator arguments

Table 19.1. Performance Profile Creator arguments

Argument	Description
disable-ht	Disable hyperthreading. Possible values: true or false . Default: false .
	WARNING If this argument is set to true you should not disable hyperthreading in the BIOS. Disabling hyperthreading is accomplished with a kernel command line argument.
info	This captures cluster information and is used in discovery mode only. Discovery mode also requires the must-gather-dir-path argument. If any other arguments are set they are ignored. Possible values: • log • JSON
	NOTE These options define the output format with the JSON format being reserved for debugging. Default: log.
mcp-name	MCP name for example worker-cnf corresponding to the target machines. This parameter is required.

Argument	Description
must-gather-dir-path	Must gather directory path. This parameter is required. When the user runs the tool with the wrapper script must-gather is supplied by the script itself and the user must not specify it.
power-consumption- mode	The power consumption mode. Possible values: • default • low-latency • ultra-low-latency Default: default.
profile-name	Name of the performance profile to create. Default: performance .
reserved-cpu-count	Number of reserved CPUs. This parameter is required. NOTE This must be a natural number. A value of 0 is not allowed.
rt-kernel	Enable real-time kernel. This parameter is required. Possible values: true or false .
split-reserved-cpus- across-numa	Split the reserved CPUs across NUMA nodes. Possible values: true or false . Default: false .
topology-manager-policy	Kubelet Topology Manager policy of the performance profile to be created. Possible values: • single-numa-node • best-effort • restricted Default: restricted.

Argument	Description
user-level-networking	Run with user level networking (DPDK) enabled.
	Possible values: true or false .
	Default: false .

19.2. ADDITIONAL RESOURCES

• For more information about the **must-gather** tool, see Gathering data about your cluster .