

Bisleri Gate Entry App

Steps to Follow for Setup of Application

Version 2.0 | April 2026

Overview

This document describes how to set up the Bisleri Gate Entry App on a fresh machine. The project ships with a one-command setup script (setup.py) that automates the three main tasks:

- Python package installation (backend dependencies via pip)
- Database migration (Alembic upgrade — creates all 8 tables automatically)
- Frontend npm package installation (Expo / React Native)

After running the script, backend and frontend are started manually — see Sections 3 and 4 for exact commands.

NOTE: Both the server device (running the app) and the tablet/phone must be on the same network.

Section 1 — Pre-Requisites

1.1 Software Requirements

Software	Version / Notes
Python	3.9 or higher
Node.js + npm	v18 LTS or higher
PostgreSQL	v14 or higher
Expo CLI	Installed automatically by npm install
Git	For cloning the repository

1.2 Install PostgreSQL

Ensure PostgreSQL is installed on your system. You can download it from:

<https://www.postgresql.org/download/>

1.3 Create the Database

Open the PostgreSQL command line (psql) and run:

```
psql -U postgres -c "CREATE DATABASE Bisleri_01;" -W
```

Or use pgAdmin: right-click Databases → Create → Database → name it Bisleri_01.

⚠ Database name is case-sensitive in some configurations. Use exactly: Bisleri_01

1.4 Configure the .env File

Before running the setup script, update bisleri-backend/.env with your PostgreSQL credentials:

```
DATABASE_URL=postgresql://postgres:<YOUR_PASSWORD>@localhost:5432/Bisleri_01
SECRET_KEY=<your_secret_key>
ALGORITHM=HS256
ACCESS_TOKEN_EXPIRE_MINUTES=60
```

Also update gate-entry-app/.env (or the Expo config):

```
# Local development
EXPO_PUBLIC_API_URL=http://<YOUR_LOCAL_IP>:8001

# Production / server
EXPO_PUBLIC_API_URL=https://123.63.20.237:19000/api
```

Section 2 — Automated Setup (setup.py)

The project root contains `setup.py`. Run it once after cloning — it handles all three installation steps automatically:

```
python setup.py
```

2.1 What the Script Does

Step	Description
[1/3] Python packages	Runs <code>pip install -r bisleri-backend/requirements.txt</code>
[2/3] Database migrations	Runs <code>alembic upgrade head</code> inside <code>bisleri-backend/</code> — creates all 8 tables
[3/3] Frontend packages	Runs <code>npm install --legacy-peer-deps</code> inside <code>gate-entry-app/</code>

2.2 Expected Output

```
=====
Bisleri Gate Entry App — Setup
=====

[1/3] Installing Python packages ...
      Done.

[2/3] Running database migrations (Alembic) ...
      Done.

[3/3] Installing frontend npm packages ...
      Done.

=====
Setup complete!

— LOCAL DEVELOPMENT —
Backend: cd bisleri-backend
         uvicorn app.main:app --host 127.0.0.1 --port 8001 --reload

Frontend: cd gate-entry-app
         npx expo start --port 8082 -c

         . env: EXPO_PUBLIC_API_URL=http://<YOUR_LOCAL_IP>:8001

— PRODUCTION (SERVER) —
Backend: cd bisleri-backend
         uvicorn app.main:app --host 127.0.0.1 --port 8000

Frontend: cd gate-entry-app
         npx expo start --port 8081

         . env: EXPO_PUBLIC_API_URL=https://123.63.20.237:19000/api
=====
```

⚠ If [2/3] fails: Make sure PostgreSQL is running and. `env` is configured correctly.

You can run migrations manually later:
`cd bisleri-backend && alembic upgrade head`

Section 3 — Database Schema (schema.sql)

Alembic applies all migrations automatically via setup.py. For reference, the schema.sql file in the project root documents the complete database structure. The schema creates 8 tables:

#	Table	Purpose
1	location_master	Warehouse / site master — synced from Mfabric ERP
#	Table Name	Purpose
1	location_master	Warehouse / site master — synced from Mfabric ERP
2	users_master	App users: security guards, security admins, IT admin
3	insights_data	Central FG gate-entry log (Gate-In / Gate-Out) with 3-colour edit system
4	document_data	Consolidated ERP document index (built by data-sync service)
5	mfabric_deliverychallan_data	Staging — raw Mfabric Delivery Challan sync
6	mfabric_invoice_data	Staging — raw Mfabric Invoice sync
7	mfabric_transferorder_rgp_data	Staging — raw Mfabric Transfer Order / RGP sync
8	raw_materials_data	Gate-entry log for Raw Material vehicles (separate from FG)

3.1 Key Table Details

location_master

Stores 555 real warehouse/site records pre-loaded from the Warehouse Master. Synced from Mfabric — do not manually edit rows. Primary key: warehouse_code.

users_master

Application users with roles: securityguard | securityadmin | itadmin. Passwords are stored as bcrypt hashes (generated by passlib CryptContext). A default IT Admin account is seeded automatically.

insights_data (FG Gate Entry Log)

Every Finished Goods vehicle movement (Gate-In / Gate-Out) creates one row. Implements the 3-colour edit system:

- YELLOW — entry needs completion (driver_name, km_reading, loader_names missing)
- GREEN — all required fields filled within 48-hour window
- BLACK — 48-hour edit window has expired

Gate entry numbers follow the format: GATE-YYYYMMDD-NNNN (generated by the frontend).

raw_materials_data (RM Gate Entry Log)

Separate log for Raw Material vehicles. All fields (party name, material description, quantity) must be entered manually. Applies the same 48-hour edit window logic as insights_data.

3.2 Seed Data

The schema.sql seeds the following data automatically on first run:

- 555 warehouse records across all Indian states/regions in location_master
- Default IT Admin user (see credentials below)

Default IT Admin Login

Username: itadmin

Password: Admin@123

⚠ CHANGE THIS PASSWORD immediately after first login via Admin → Reset Password

3.3 Manual Schema Run (if needed)

If you prefer to apply the schema manually instead of using Alembic:

```
psql -U postgres -d Bisleri_01 -f schema.sql -W
```

Section 4 — Running the Application

4.1 Local Development

Open VS Code and two terminal windows:

Terminal 1 — Backend

```
cd bisleri-backend
uvicorn app.main:app --host 127.0.0.1 --port 8001 --reload
```

Successful startup shows:

```
INFO:      Waiting for application startup.
INFO:      Application startup complete.
INFO:      Uvicorn running on http://127.0.0.1:8001
```

Terminal 2 — Frontend

```
cd gate-entry-app
npx expo start --port 8082 -c
```

Local. env: EXPO_PUBLIC_API_URL=http://<YOUR_LOCAL_IP>:8001

4.2 Production / Server

Backend

```
cd bisleri-backend
uvicorn app.main:app --host 127.0.0.1 --port 8000
```

Frontend

```
cd gate-entry-app
npx expo start --port 8081
```

Production. env: EXPO_PUBLIC_API_URL=https://123.63.20.237:19000/api

4.3 IP Address Configuration

Both devices must be on the same network. To find your IPv4 address:

```
ipconfig
```

Update the following files with your IPv4 address:

- bisleri-backend/. env — DATABASE_URL and any CORS origin settings
- gate-entry-app/. env — EXPO_PUBLIC_API_URL=http://<YOUR_IP>:8001

Section 5 — Credentials & Testing

5.1 Default Login Credentials

Role	Username	Password	Notes
IT Admin	itadmin	Admin@123	Change immediately after first login
Security Guard (test)	guard123	guard123	Use this role to test gate entries

Role	Username	Password	Notes
IT Admin	itadmin	Admin@123	Change immediately after first login
Security Guard (test)	guard123	guard123	Use this role to test gate entries

5.2 Testing Vehicle Entries

Use the following sample vehicle numbers for testing:

MH03ES8405 MH02FG0714 TG15T3134

Before searching, update the document_date to today so the vehicle appears in the search results:

```
UPDATE document_data
SET    document_date = NOW ()
WHERE vehicle_no = 'MH03ES8405';
```

FG Gate Entry Flow

- Enter the vehicle number and click Search
- Select the document(s) you want to process and click Submit
- For a new / unknown vehicle, no documents will be found — use Manual Entry, then Submit
- In FG Insights you can filter records by date to view submitted entries

RM Gate Entry Flow

- All fields must be filled manually (party name, material, quantity, etc.)
- Data is saved directly to raw_materials_data in the backend

Section 6 — Important Notes

- Ensure PostgreSQL service is running before executing setup.py or starting the backend
- Both the server device and the tablet/phone must be on the same network
- Change the default itadmin password immediately after first login
- The 48-hour edit window applies to both FG (insights_data) and RM (raw_materials_data) entries
- The Mfabric staging tables (delivery challan, invoice, transfer order) are populated by the data-sync service — do not insert into them manually
- All timestamps are stored in UTC; display conversion is handled by the frontend
- Scan the QR code shown in the Expo terminal from the tablet to open the app

— End of Document —