19.5. LABS



Exercise 19.1: Managing Swap Space

Examine your current swap space by doing:

\$ cat /proc/swaps

```
Filename Type Size Used Priority /dev/sda11 partition 4193776 0 -1
```

We will now add more swap space by adding either a new partition or a file. To use a file we can do:

```
$ dd if=/dev/zero of=swpfile bs=1M count=1024

1024+0 records in
1024+0 records out
1073741824 bytes (1.1 GB) copied, 1.30576 s, 822 MB/s
$ mkswap swpfile
```

Setting up swapspace version 1, size = 1048572 KiB no label, UUID=85bb62e5-84b0-4fdd-848b-4f8a289f0c4c

(For a real partition just feed **mkswap** the partition name, but be aware all data on it will be erased!)

Activate the new swap space:

```
$ sudo swapon swpfile
swapon: /tmp/swpfile: insecure permissions 0664, 0600 suggested.
swapon: /tmp/swpfile: insecure file owner 500, 0 (root) suggested.
```



On RedHat / CentOS

Notice RHEL 7 warns us we are being insecure, we really should fix with:

```
$ sudo chown root:root swpfile
$ sudo chmod 600 swpfile
```

and ensure it is being used:

\$ cat /proc/swaps

 Filename
 Type
 Size
 Used
 Priority

 /dev/sda11
 partition
 4193776
 0
 -1

 /tmp/swpfile
 file
 1048572
 0
 -2

Note the Priority field; swap partitions or files of lower priority will not be used until higher priority ones are filled.

Remove the swap file from use and delete it to save space:

```
$ sudo swapoff swpfile
$ sudo rm swpfile
```

LFS201: V_2018-12-25

