Concept of Operating Systems

☐ A computer system can be divided roughly into four components: the hardware, the operating system, the application programs, and a user




Figure 1.1 Abstract view of the components of a computer system.

☐ The hardware— the central processing unit (CPU), the memory, and the input/output (I/O) devices—provides the basic computing resources for the system. ☐ The application programs—such as word processors, spreadsheets, compilers, and web browsers—define the ways in which these resources are used to solve users' computing problems. ☐ The operating system controls the hardware and coordinates its use among the various application programs for the various users. ☐ We next explore operating systems from two viewpoints: that of the user and that of the system. ☐ User View ☐ The user's view of the computer varies according to the interface being used. ☐ Many computer users sit with a laptop or in front of a PC consisting of a monitor, keyboard, and mouse. ☐ In this case, the operating system is designed mostly for ease

of use, with some attention paid to performance and security

	and none paid to resource utilization—how various hardware
	and software resources are shared.
	 Many users interact with mobile devices such as smartphones and tablets
	 The user interface for mobile computers generally features a touch screen
	☐ Many mobile devices also allow users to interact through a
	voice recognition interface, such as Apple's Siri.
	☐ Some computers have little or no user view. For example,
	embedded computers in home devices and automobiles -
	designed primarily to run without user intervention.
	□ System View
	In this context, we can view an operating system as a resource allocator.
	☐ A computer system has many resources that may be required
	to solve a problem: CPU time, memory space, storage space,
	I/O devices, and so on.
	☐ The operating system acts as the manager of these resources.
De	efining Operating Systems
	☐ The fundamental goal of computer systems is to execute programs and to make solving user problems easier.
	☐ Since bare hardware alone is not particularly easy to use, application
	programs are developed.
	☐ These programs require certain common operations, such as those
	controlling the I/O devices.
	☐ The common functions of controlling and allocating resources are
	then brought together into one piece of software: the operating
	system.
	□ operating system is the one program running at all times on the
	computer—usually called the kernel .
	☐ Along with the kernel, there are two other types of programs: system
	programs and application programs

 System programs - associated with the operating system but are not necessarily part of the kernel Application programs - include all programs not associated with the operation of the system. Mobile operating systems often include not only a core kernel but also middleware—a set of software frameworks that provide additional services to application developers. An operating system (OS) functions as a mediator between application programs, utilities, users, and the computer hardware
BASIC ELEMENTS OF A COMPUTER:
□ A computer consists of processor, memory, I/O components and system bus
□ Processor: It Controls the operation of the computer and performs its data processing functions. When there is only one processor, it is often referred to as the central processing unit
■ Main memory: It Stores data and programs. This memory is typically volatile; that is, when the computer is shut down, the contents of the memory are lost. Main memory is also referred to as real memory or primary memory
□ I/O modules : It moves data between the computer and its external environment. The external environment consists of a variety of devices, including secondary memory devices (e. g., disks), communications equipment, and terminals
 System bus: It provides the communication among processors, main memory, and I/O modules





Figure 1.1 Computer Components: Top-Level View

- ☐ One of the processor's functions is to exchange data with memory. For this purpose, it typically makes use of two internal registers
- ☐ A memory address registers (MAR), which specifies the address in memory for the next read or write
- ☐ A memory buffer register (MBR), which contains the data to be written into memory or which receives the data read from memory
- ☐ An I/O address register (I/OAR) specifies a particular I/O device
- ☐ An I/O buffer register (I/OBR) is used for the exchange of data between an I/O module and the processor

	A memory module consists of a set of locations, defined by
S	sequentially numbered addresses.
	An I/O module transfers data from external devices to processor and
r	memory, and vice versa. It contains internal buffers for temporarily
r	nolding data until they can be sent on
	PROCESSOR REGISTERS provide memory that is faster and smaller
t	han main memory. Processor registers serve two functions
□ 1	I.User-visible registers: Enable the machine or assembly language
þ	programmer to minimize main memory references by optimizing
r	register use
$\Box A$	A user-visible register is generally available to all programs, including
a	application programs as well as system programs
	The types of User visible registers are
	$\hfill\square$ Data Registers - can be used with any machine instruction that
	performs operations on data
	☐ Address Registers - contain main memory addresses of data
	and instructions
	2.Control and status register:
	☐ A variety of processor registers are employed to control the
	operation of the processor
	□ MAR, MBR, IOAR, IOBR
	☐ Instruction register (IR): It contains the instruction most
	recently fetched
	□ Program counter (PC): Contains the address of the next
	instruction to be fetched
	UCTION EXECUTION:
	A program to be executed by a processor consists of a set of
	nstructions stored in Memory. The instruction processing consists of
	wo steps
	The processor reads (fetches) instructions from memory one at a
	ime (fetch stage)
	Execute the instruction.(execute stage)
	The processing required for a single instruction is called an nstruction cycle
	nsimichon cycle



EVOLUTION OF OPERATING SYSTEM (or) Generations of OS (or) Types of OS

1. Serial processing [First Generation]

During 1940s to the mid-1950s, the programmer interacted directly with the
computer hardware; there was no OS
Programs in machine code were loaded via the input device (e.g., a card reader)
If an error halted the program, the error condition was indicated by the lights
If the program proceeded to a normal completion, the output appeared on the printer
These early systems presented two main problems:
1.Scheduling
☐ Most installations used a hardcopy sign-up sheet to reserve computer time
☐ A user might sign up for an hour and finish in 45 minutes
☐ On the other hand, the user might run into problems, not finish in the
allotted time, and be forced to stop before resolving the problem
2.Setup time
☐ A single program, called a job , could involve loading the compiler plus
the high-level language program (source program) into memory
☐ saving the compiled program (object program)
then loading and linking together the object program and common functions








2. Simple Batch Systems [Second Generation]

☐ In 1970's	
☐ The central idea behind the simple batch-processing scheme is the use	e of a piece
of software known as the monitor	
☐ the user no longer has direct access to the processor	

- user submits the job on cards or tape to a computer operator, who batches the jobs together sequentially and places the entire batch on an input device, for use by the monitor
- ☐ Each program is constructed to branch back to the monitor when it completes processing, and the monitor automatically begins loading the next program








Memory Layout for a Resident Monitor


The monitor controls the sequence of events. For this the monitor must always be
in main memory and available for execution. That portion is referred to as the
resident monitor

☐ The monitor reads in jobs one at a time from the input device .As it is read in, the current job is placed in the user program area, and control is passed to this job


		Once a job has been read in, the processor will encounter a branch instruction in
		the monitor that instructs the processor to continue execution at the start of the
		user program. The processor will then execute the instructions in the user program until it encounters an ending or error condition
		The monitor performs a scheduling function: A batch of jobs is queued up, and
		jobs are executed as rapidly as possible, with no intervening idle time
		With each job, instructions are included in a form of job control language (JCL)
		which are denoted by the beginning \$. This is a special type of programming
		language used to provide instructions to the monitor The overall format of the job is given as
		The overall format of the job is given as
		ė i o p
		\$JOB \$FTN
		•)
		FORTRAN instructions
		•)
		\$LOAD
		\$RUN
		• Data
		• J
	П	\$END
		The memory protection leads to the concept of dual mode operation: User mode
		and Kernel Mode
3.	Multi	programmed Batch Systems[Third Generation]
		Even in simple batch operating system, the processor is often idle. The problem is
		that I/O devices are slow compared to the processor
		Let us consider a program that processes a file of records and performs, on
		average, 100 machine instructions per record. The computer spends over 96% of
		its time waiting for I/O devices to finish transferring data to and from the file



☐ In uniprogramming we will have a single program in the main memory. The processor spends a certain amount of time executing, until it reaches an I/O instruction. It must then wait until that I/O instruction concludes before proceeding. This inefficiency is not necessary



☐ In Multiprogramming we will have an OS and more user programs. When one job needs to wait for I/O, the processor can switch to the other job, which is likely not waiting for I/O. This approach is known as **multiprogramming**, **or multitasking**




4. Time-Sharing Systems[Third Generation]

In time sharing systems the processor time is shared among multiple users
multiple users simultaneously access the system through terminals, with the OS
interleaving the execution of each user program in a short burst or quantum of
computation
If there are n users actively requesting service at one time, each user will only see
on the average 1/n of the effective computer capacity

Batch Multiprogramming Vs Time Sharing systems

	Batch Multiprogramming	Time Sharing
Principal objective	Maximize processor use	Minimize response time
Source of directives to operating system	Job control language commands provided with the job	Commands entered at the terminal

Source of directives to operating system	Job control language commands provided with the job	Commands entered at the terminal
One of the first time-sharing	operating systems to be developed	was the
Compatible Time-Sharing Sy	1 0 1	
The system ran on a compute	er with 32,000 36-bit words of mai	n memory, with
	ing 5000 of that. When control was program and data were loaded intry	•
A program was always loade	d to start at the location of the 500	0th word
A system clock generated int seconds	errupts at a rate of approximately of	one every 0.2
At each clock interrupt, the Canother user. This technique	OS regained control and could assign is known as time slicing	gn the processor to
Example: Assume that the	re are four interactive users with the	ne following memory
requirements, in words:		
	JOB1: 15,000	
	JOB2: 20,000	
	JOB3: 5000	
	JOB4: 10,000	



i) Initially, the monitor loads JOB1 and transfers control to it.

- Later, the monitor decides to transfer control to JOB2. Because JOB2 requires more memory than JOB1, JOB1 must be written out first, and then JOB2 can be loaded.
- iii) Next, JOB3 is loaded in to be run. However, because JOB3 is smaller than JOB2, a portion of

JOB2 can remain in memory, reducing disk write time.

- iv) Later, the monitor decides to transfer control back to JOB1. An additional portion of JOB2 must be written out when JOB1 is loaded back into memory.
- v) When JOB4 is loaded, part of JOB1 and the portion of JOB2 remaining in memory are retained.
- vi) At this point, if either JOB1 or JOB2 is activated, only a partial load will be required. In this example, it
- is JOB2 that runs next. This requires that JOB4 and the remaining resident portion of JOB1 be written out and that the missing portion of JOB2 be read in.

5. MULTIPROCESSOR AND MULTICORE ORGANIZATION[Fourth Generation]

A processor executes programs by executing machine instructions in sequence and one at a time. Each instruction is executed in a sequence of operations (fetch instruction, fetch operands, perform operation, store results)

☐ In order to achieve performance and reliability, the concept of parallelism has been introduced in the computers which include symmetric multiprocessors, multicore computers and clusters.
 ☐ The multiple-processor systems in use today are of two types. ☐ Asymmetric multiprocessing, in which each processor is assigned a specific task. A boss processor, controls the system; the other processors either look to the boss for instruction or have predefined tasks. This scheme defines a boss—worker relationship. The boss processor schedules and allocates work to the worker processors. ☐ Symmetric multiprocessing (SMP), in which each processor performs all tasks
within the operating system. SMP means that all processors are peers; no boss—worker relationship exists between processors.
Symmetric Multiprocessors:
☐ An SMP can be defined as a stand-alone computer system with the following
characteristics:
1. There are two or more similar processors of comparable capability.
2. These processors share the same main memory and I/O facilities and are
interconnected by a bus or other internal connection scheme, such that memory access
time is approximately the same for each processor.
3. All processors share access to I/O devices, either through the same channels or
through different channels that provide paths to the same device.
4. All processors can perform the same functions 5. The system is controlled by an integrated energing system that provides
5. The system is controlled by an integrated operating system that provides interaction between processors and their programs at the job, task, file, and data element
levels.
☐ Advantages of Symmetric multiprocessors:
1. Increased throughput.
By increasing the number of processors, we expect to get more work done in less time.
If the work to be done by a computer can be organized so that some portions of the work can be done in parallel, then a system with multiple processors will yield greater performance than one with a single processor of the same type
☐ 2. Economy of scale. Multiprocessor systems can cost less than equivalent multiple
single-processor systems, because they can share peripherals, mass storage, and power supplies. If several programs operate on the same set of data, it is cheaper to store those data on one disk and to have all the processors share them than to have many computers
with local disks and many copies of the data.
☐ 3. Increased reliability. If functions can be distributed properly among several
processors, then the failure of one processor will not halt the system, only slow it down. If we have ten processors and one fails, then each of the remaining nine processors can pick up a share of the work of the failed processor. Thus, the entire system runs slower.

rather than failing altogether. Increased reliability of a computer system is crucial in many applications.

☐ The ability to continue providing service proportional to the **level of surviving hardware** is called **Graceful Degradation**. Some systems go beyond graceful degradation and are called **fault tolerant**, because they can suffer a failure of any single component and still continue operation.




Figure 1.6 Symmetric multiprocessing architecture.

☐ The Disadvantage of symmetric multiprocessor includes

- 1) If one processor fails then it will affect in the speed
- 2) multiprocessor systems are expensive
- 3) Complex OS is required
- 4) Large main memory required.

MULTICORE ORGANIZATION

- A dual-core design contains two cores on the same chip.
- ☐ In this design, each core has its own register set as well as its own local cache. Other designs might use a shared cache or a combination of local and shared caches.
- Performance has also been improved by the increased complexity of processor design to exploit parallelism in instruction execution and memory access.





Figure 1.7 A dual-core design with two cores placed on the same chip.

An example of a multicore system is the Intel Core i7, which includes four x86 processors, each with a dedicated L2 cache, and with a shared L3 cache Difference between Multiprocessor and Multicore ☐ The main difference between multiprocessor and multicore systems lies in their hardware structure. ☐ Multicore systems have multiple processing units (cores) integrated onto a single integrated circuit (chip), while multiprocessor systems have multiple separate physical processors, each with its own core, connected to the same motherboard. 6. Distributed Systems ☐ A distributed system is a collection of physically separate, possibly heterogeneous computer systems that are networked to provide users with access to the various resources that the system maintains ☐ Access to a shared resource increases computation speed, functionality, data availability, and reliability ☐ Some operating systems generalize network access as a form of file access, with the details of networking contained in the network interface's device driver ☐ Others make users specifically invoke network functions ☐ Generally, systems contain a mix of the two modes—for example FTP and NFS ☐ A network, in the simplest terms, is a communication path between two or more systems. ☐ Distributed systems depend on networking for their functionality ☐ Independent Nodes - Each computer in the distributed system has its own operating system and local resources

☐ Communication Network These nodes are connected through a network (LAN,


WAN, etc.), enabling them to communicate and exchange information

	Distributed OS Software:
	The distributed operating system software manages the interaction and coordination between these nodes, presenting a unified view to the user.
□ F	Resource Sharing:
	It allows users and applications to access resources (like CPU, memory, storage, and peripherals) on any node in the network as if they were local.
	Transparency:
	DOS aims to hide the underlying distribution of resources, making it appear as if the system is a single, centralized machine
	Scalability:
[DOS systems are designed to be scalable, meaning they can easily accommodate the addition of new nodes without significant disruption.
□ F	Fault Tolerance:
	By distributing tasks and resources across multiple nodes, DOS can continue functioning even if some nodes fail.
7 Not	work Operating Systems
7. Net	work Operating Systems
	work Operating Systems ATING SYSTEM STRUCTURE
OPER	ATING SYSTEM STRUCTURE The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures.
OPER	The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure
OPER	The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure Layered approach
OPER	ATING SYSTEM STRUCTURE The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure Layered approach Microkernels
OPER	The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure Layered approach Microkernels Modules
OPER	The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure Layered approach Microkernels Modules Hybrid systems
OPER i i Simple	The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure Layered approach Microkernels Modules Hybrid systems structure: The Simple structured operating systems do not have a well defined structure. These systems will be simple, small and limited systems.
OPER i i Simple	The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure Layered approach Microkernels Modules Hybrid systems structure: The Simple structured operating systems do not have a well defined structure. These systems will be simple, small and limited systems. le: MS-DOS.
OPER i i i i i i i i i i i i i i i i i i	The operating systems are large and complex. A common approach is to partition the task into small components, or modules, rather than have one monolithic system. The structure of an operating system can be defined as the following structures. Simple structure Layered approach Microkernels Modules Hybrid systems structure: The Simple structured operating systems do not have a well defined structure. These systems will be simple, small and limited systems.




Example: Traditional UNIX OS

- ☐ It consists of two separable parts: the kernel and the system programs.
- ☐ The kernel is further separated into a series of interfaces and device drivers
- ☐ The kernel provides the file system, CPU scheduling, memory management, and other operating-system functions through system calls.
- ☐ This **monolithic structure** was difficult to implement and maintain.




Layered approach:


A system can be made modular in many ways. One method is the **layered approach**, in which the operating system is broken into a number of layers (levels). The bottom layer (layer 0) is the hardware; the highest (layer N) is the user interface.



☐ An operating-system layer is an implementation of an abstract object made up of data and the operations that can manipulate those data.
☐ The main advantage of the layered approach is simplicity of construction and debugging. The layers are selected so that each uses functions (operations) and services of only lower-level layers.
☐ Each layer is implemented only with operations provided by lower-level layers. A layer does not need to know how these operations are implemented; it needs to know only what these operations do.
☐ The major difficulty with the layered approach involves appropriately defining the various layers because a layer can use only lower-level layers.
☐ A problem with layered implementations is that they tend to be less efficient than other types.
licrokernels:
☐ In the mid-1980s, researchers at Carnegie Mellon University developed an operating system called Mach that modularized the kernel using the microkernel approach.
☐ This method structures the operating system by removing all nonessential components from the kernel and implementing them as system and user-level programs.




☐ Microkernel provide minimal process and memory management, in addition to a communication facility.
☐ The main function of the microkernel is to provide communication between the client program and the various services that are also running in user space.
☐ The client program and service never interact directly. Rather, they communicate indirectly by exchanging messages with the microkernel.
☐ One benefit of the microkernel approach is that it makes extending the operating system easier. All new services are added to user space and consequently do not require modification of the kernel.
☐ The performance of microkernel can suffer due to increased system-function overhead.
Modular Structure
☐ The best current methodology for operating-system design involves using loadable kernel modules
☐ The kernel has a set of core components and links in additional services via modules, either at boot time or during run time.
☐ The kernel provides core services while other services are implemented dynamically, as the kernel is running.
☐ Linking services dynamically is more comfortable than adding new features directly to the kernel, which would require recompiling the kernel every time a change was made.
Example: Solaris OS



	The Solaris operating system structure is organized around a core kernel with seven types
	of loadable kernel modules:
	☐ Scheduling classes
	☐ File systems
	☐ Loadable system calls
	☐ Executable formats
	☐ STREAMS modules
	☐ Miscellaneous
	☐ Device and bus drivers
Hybri	d Systems:
	The Operating System combines different structures, resulting in hybrid systems that address performance, security, and usability issues.
	They are monolithic, because having the operating system in a single address space provides very efficient performance.
	However, they are also modular, so that new functionality can be dynamically added to the kernel.
	Example: Linux and Solaris are monolithic (simple) and also modular, IOS. Apple IOS Structure

Structure Type	Description	Examples
Monolithic Kernel	All core services run in kernel space for speed	Linux, older UNIX
Microkernel	Minimal kernel; services run in user space	QNX, seL4
Hybrid Kernel	Mix of monolithic and microkernel features	Windows NT, macOS
Modular Structure	Kernel with loadable modules for flexibility	Linux, Solaris
Layered Structure	OS divided into layers with clear interfaces	UNIX (partially)
Virtual Machines	OS runs on virtualized hardware	VMware, Hyper-V

SYSTEM CALLS



The caller of the system call knows nothing about how the system call is implemented or
what it does during execution.
The caller need only obey the API and understand what the operating system will do as a
result of the execution of that system call.





Figure 2.6 The handling of a user application invoking the open() system call.

☐ Three general methods are used to pass parameters to the operating system
pass the parameters in registers
parameters are generally stored in a block, or table, in memory, and the address of
the block is passed as a parameter in a register
☐ Parameters also can be placed, or pushed , onto the stack by the program and
popped off the stack by the operating system.
Types of System Calls:
☐ System calls can be grouped roughly into six major categories
□ Process control,
□ File manipulation,
□ Device manipulation,
☐ Information maintenance,
□ Communications,
□ Protection.
PROCESS CONTROL
☐ A Running program needs to be able to halt its execution either normally (end ()) or abnormally (abort()).
☐ Under either normal or abnormal circumstances, the operating system must transfer control to the invoking command interpreter.
☐ A process or job executing one program may want to load() and execute() another program. This feature allows the command interpreter to execute a program as directed by, for example, a user command, the click of a mouse, or a batch command.



- ☐ If we create a new job or process, or perhaps even a set of jobs or processes, we should be able to control its execution that requires to determine and reset the attributes of a job or process, including the job's priority, its maximum allowable execution time, and so on (get process attributes() and set process attributes()).

 ☐ We may also want to terminate a job or process that we created (terminate process()) if we find that it is incorrect or is no longer needed.

 ☐ The System -calls associated with process control includes

 end, abort

 load, execute

 create process, terminate process

 get process attributes, set process attributes

 Wait for time

 wait event, signal event

 allocate and free memory

 ☐ When a process has been created, we may want to wait for a certain amount of time to pass (wait time()) or we will want to wait for a specific event to occur (wait event())
- pass (wait time()) or we will want to wait for a specific event to occur (wait event()).

 ☐ The jobs or processes should then signal when that event has occurred (signal event())

 ☐ To start a new process, the shell executes a fork() system call. Then, the selected program is loaded into memory via an exec() system call, and the program is executed

 ☐ When the process is done, it executes an exit() system call to terminate, returning to the

FILE MANAGEMENT


- ☐ In order to work with files, we first need to be able to **create ()** and **delete ()** files. Either system call requires the name of the file and perhaps some of the file's attributes. Once the file is created, we need to **open()** it and to use it.
- ☐ We may also **read** (), **write** (), or **reposition** (). Finally, we need to **close** () the file, indicating that we are no longer using it.

invoking process a status code of 0 or a nonzero error code.

☐ In addition, for either files or directories, we need to be able to determine various attributes and perhaps to reset them if necessary.	the values of
File attributes include the file name, file type, protection codes, accounting	na information
and so on. At least two system calls, getfileattributes () and setfileattrib	-
required for this function.	utes (), are
☐ The System calls associated with File management includes	
☐ File management	
☐ create file, delete file	
open, close	
read, write, reposition	
get file attributes, set file attributes	
DEVICE MANAGEMENT:	
☐ A process may need several resources to execute—main memory, disk dr.	ives, access to
files, and so on. If the resources are available, they can be granted, and co	
returned to the user process. Otherwise, the process will have to wait until	il sufficient
resources are available.	
☐ A system with multiple users may require us to first request() a device, to	o ensure
exclusive use of it.	
☐ After we are finished with the device, we release() it. These functions are	e similar to the
open() and close() system calls for files.	1 (:1-1)
Once the device has been requested (and allocated to us), we can read() , write() , reposition() the device, just as we can with files.	, and (possibly)
☐ I/O devices are identified by special file names, directory placement, or f	file attributes
☐ The System calls associated with Device management includes	ine attitutes.
request device, release device	
• read, write, reposition	
 get device attributes, set device attributes 	
 logically attach or detach devices 	
INFORMATION MAINTENANCE:	
☐ Many system calls exist simply for the purpose of transferring information	n between the
user program and the operating system.	
Example, most systems have a system call to return the current time() are	9
Other system calls may return information about the system, such as the r	
current users, the version number of the operating system, the amoun	nt of free
memory or disk space, and so on.	unaful for
☐ Many systems provide system calls to dump() memory. This provision is debugging.	userur ror
☐ Many operating systems provide a time profile of a program to indicate	the amount of
time that the program executes at a particular location or set of locations.	
☐ The operating system keeps information about all its processes, and sy	
used to access this information.	
☐ Generally, calls are also used to reset the process information (get proces	ss attributes()
and set process attributes()).	<u> </u>
☐ The System calls associated with Device management includes	

☐ get time or date, set time or date ☐ get system data, set system data ☐ get process, file, or device attributes
☐ set process, file, or device attributes COMMUNICATION:
There are two common models of Interprocess communication: the message passing model and the shared-memory model.
In the message-passing model, the communicating processes exchange messages with one another to transfer information.
 Messages can be exchanged between the processes either directly or indirectly through a common mailbox.
Each process has a process name , and this name is translated into an identifier by which the operating system can refer to the process. The get hostid() and get processid() system calls do this translation.
☐ The recipient process usually must give its permission for communication to take place with an accept connection () call.
☐ The source of the communication, known as the client , and the receiving daemon, known as a server , then exchange messages by using read message() and write message() system calls.
☐ The close connection() call terminates the communication
☐ In the shared-memory model , processes use shared memory create() and shared memory attach() system calls to create and gain access to regions of memory owned by other processes.
☐ The system calls associated with communication includes, ∘ create, delete communication connection ∘ send, receive messages ∘ Transfer status information ∘ attach or detach remote devices
PROTECTION:
☐ Protection provides a mechanism for controlling access to the resources provided by a computer system.
☐ System calls providing protection include set permission () and get permission (), which manipulate the permission settings of resources such as files and disks.
☐ The allow user () and deny user () system calls specify whether particular users can—or cannot—be allowed access to certain resources.
Operating-System Services
$\hfill\Box$ An OS provides certain services to programs and to the users of those programs $\hfill\Box$
☐ 1. Services helpful to the user
☐ User interface


Almost all OS have interface
command-line interface (CLI) - uses text commands and a method for entering
them
batch interface - commands and directives to control those commands are
entered into files, and those files are executed
graphical user interface (GUI) - the interface is a window system with a pointing
device to direct I/O, choose from menus, and make selections and a keyboard to
enter text
Program Execution
The system must be able to load a program into memory and to run that program
The program must be able to end its execution, either normally or abnormally




□ I/O operations
 □ A running program may require I/O, which may involve a file or an I/O device
 □ special functions may be desired (such as recording to a CD or DVD drive or blanking a display screen)
 □ users usually cannot control I/O devices directly
 □ the operating system must provide a means to do I/O
 □ File-system manipulation
 □ programs need to read and write files and directories
 □ need to create and delete them by name, search for a given file, and list file information

permissions management to allow or deny access to files or directories based on file ownership
provide a variety of file systems, for specific features or performance characteristics
Communications
one process needs to exchange information with another process
may occur between processes that are executing on the same computer or between processes that are executing on different computer systems tied together by a computer network
implemented via
 shared memory - two or more processes read and write to a shared section of memory
 message passing - packets of information in predefined formats are moved between processes by the operating system
Error detection
The operating system needs to be detecting and correcting errors constantly
Errors may occur in the
☐ CPU
☐ Memory hardware (mem. Error or power failure)
 I/O devices (such as a parity error on disk, a connection failure on a network, or lack of paper in the printer)
 user program (such as an arithmetic overflow, an attempt to access an illegal memory location, or a too-great use of CPU time)
For each type of error, the operating system should take the appropriate action to ensure correct and consistent computing
☐ Sometimes, it has no choice but to halt the system
 At other times, it might terminate an error-causing process or return an error code to a process for the process to detect and possibly correct
2. Services for ensuring the efficient operation of the system
Resource allocation
When there are multiple users or multiple jobs running at the same time,
resources must be allocated to each of them
types of resources
☐ CPU cycles
☐ main memory
☐ file storage
☐ I/O devices
Accounting

	record keeping
	☐ which users use how much and what kinds of computer resources
] for accumulating usage statistics
	to reconfigure the system
	to improve computing services
	Protection and security
	The owners of information stored in a multiuser or networked computer system may want to control use of that information
	it should not be possible for one process to interfere with the others or with the operating system itself
	ensuring that all access to system resources is controlled
	requiring each user to authenticate, through password
	ward Orangting Orantana Intentant
_	r and Operating-System Interface
	The second of the second of
	1. Command Interpreters
	Some operating systems include the command interpreter in the kernel
	Others, such as Windows and UNIX, treat the command interpreter
	as a special program that is running when a job is initiated or when a
	user first logs on
	On systems with multiple command interpreters to choose from, the interpreters are known as shells
	on UNIX and Linux systems, a user may choose among several
	different shells, including the Bourne shell, C shell, Bourne-Again shell, Korn shell, and others





	2. — implements most commands through system programs. In this
	case, the command interpreter does not understand the command in any way
	the UNIX command to delete a file rm file.txt would search for a file
_	called rm, load the file into memory, and execute it with the parameter
	file.txt
	In this way, programmers can add new commands to the system
	easily by creating new files
	2. Graphical User Interfaces
	users employ a mouse-based window-and-menu system characterized by a desktop metaphor
	The user moves the mouse to position its pointer on images, or
	icons , (represent programs, files, directories, and system functions)
	on the screen
	clicking a button on the mouse can invoke a program, select a file or
	directory—known as a folder
	Because a mouse is impractical for most mobile systems,
	smartphones and handheld tablet computers typically use a
	touchscreen interface
	users interact by making gestures on the touchscreen —for example,
	pressing and swiping fingers across the screen
Syst	em Programs
•	System programs, also known as system utilities, provide a
	convenient environment for program development and execution
	Some of them are simply user interfaces to system calls
	Categories
	File management
	These programs create, delete, copy, rename, print, dump, list, and
	generally manipulate files and directories
	Status information
	Some programs simply ask the system for the date, time, amount of
	available memory or disk space, number of users, or similar status
	information

☐ Others are more complex, providing detailed performance, logging, and debugging information
☐ Some systems also support a registry, which is used to store and retrieve configuration information
☐ File modification
☐ Several text editors may be available to create and modify the content of files stored on disk or other storage devices
☐ There may also be special commands to search contents of files or perform transformations of the text
□ Programming-language support
☐ Compilers, assemblers, debuggers, and interpreters for common programming languages (such as C, C++, Java, and PERL) are often provided with the operating system or available as a separate download
☐ Program loading and execution
□ Once a program is assembled or compiled, it must be loaded into memory to be executed.
☐ The system may provide absolute loaders, relocatable loaders, linkage editors, and overlay loaders.
☐ Debugging systems for either higher-level languages or machine language are needed as well
□ Communications
 provide the mechanism for creating virtual connections among processes, users, and computer systems
□ allow users to send messages to one another's screens, to browse Web pages, to send e-mail messages, to log in remotely, or to transfer files from one machine to another
□ Background services
☐ All general-purpose systems have methods for launching certain system-program processes at boot time
☐ Some of these processes terminate after completing their tasks, while others continue to run until the system is halted
☐ Constantly running system-program processes are known as services, subsystems, or daemons

Operating-System Design and Implementation ☐ We discuss problems we face in designing and implementing an operating system □ Design Goals ☐ At the highest level, the design of the system will be affected by the ☐ choice of hardware and the □ type of system: batch, time sharing, single user, multiuser, distributed, real time, or general purpose ☐ The requirements can, however, be divided into two basic groups ☐ user goals ☐ The system should be convenient to use, easy to learn and to use, reliable, safe, and fast □ system goals □ easy to design, implement, and maintain; and it should be flexible, reliable, error free, and efficient ☐ There is not a unique solution in the creation and design of operating systems, but the principles of software engineering can be taken as guidance □ Principles □ 1.Mechanisms and Policies ☐ One important principle is the separation of policy from mechanism ☐ Mechanisms determine **how to do** something(eg. Timer construct to provide protection) ☐ Policies determine **what will be done**(eg.How long the timer is set for a user) ☐ Policies are likely to change across places or over time □ each change in policy would require a change in the underlying mechanism ☐ A general mechanism insensitive to changes in policy would be more desirable ☐ A change in policy would then require redefinition of only certain parameters of the system ☐ Eg. Mechanism - Giving priority to certain programs, Policy - Can support either Priority to CPU-intensive or I/O intensive programs

Policy decisions are important for all resource allocation
Whenever it is necessary to decide whether or not to allocate a
resource, a policy decision must be made
2.Implementation
operating systems are collections of many programs, written by many people over a long period of time
Early operating systems were written in assembly language.
Now, although some operating systems are still written in assembly
language, most are written in a higher-level language such as C or an even higher-level language such as C++
an operating system can be written in more than one language.
The lowest levels of the kernel might be assembly language.
Higher-level routines might be in C, and system programs might be in
C or C++, in interpreted scripting languages like PERL or Python, or
in shell scripts
Advantages of using a higher-level language for implementing
operating systems
☐ the code can be written faster
☐ is more compact
\square easier to understand and debug
☐ improvements in compiler technology will improve the
generated code for the entire operating system by simple recompilation
 operating system is far easier to port—to move to some other hardware
Disadvantages of implementing an operating system in a higher-level
language
□ reduced speed
☐ increased storage requirements
no longer a major issue in today's systems
☐ a modern compiler can perform complex analysis and apply
sophisticated optimizations that produce excellent code
☐ Modern processors have deep pipelining and multiple functional
units




Figure 3.1 Process in memory.


□ A program is a passive entity, such as a file containing a list of instructions stored on disk(often called an executable file)
 □ a process is an active entity
 □ Two processes may be associated with the same program
 □ They are considered two separate execution sequences.
 □ The text sections are equivalent
 □ the data, heap,and stack sections vary.
 □ a process itself can be an execution environment for othercode.

- ☐ Eg. Java programming environment JVM
- ☐ to run the compiled Java program Program.class
- ☐ We enter java Program
- □ runs the JVM as an ordinary process, which in turn executes the Java program Program in the virtual machine.

MEMORY LAYOUT OF A C PROGRAM

The figure shown below illustrates the layout of a C program in memory, highlighting how the different sections of a process relate to an actual C program. This figure is similar to the general concept of a process in memory as shown in Figure 3.1, with a few differences:

- The global data section is divided into different sections for (a) initialized data and (b) uninitialized data.
- A separate section is provided for the argc and argv parameters passed to the main() function.



Process State

- ☐ The state of a process is defined in part by the current activity of that process.
- ☐ A process may be in one of the following states:
- □ **New.** The process is being created.
- ☐ **Running.** Instructions are being executed.

- ☐ **Waiting.** The process is waiting for some event to occur (such as an I/O completion or reception of a signal).
- ☐ **Ready.** The process is waiting to be assigned to a processor.
- ☐ **Terminated.** The process has finished execution.






Figure 3.2 Diagram of process state.

Process Control Block

- □ Each process is represented in the operating system by a process control block (PCB)—also called a task control block
 □ It contains many pieces of information
 □ Process state. The state may be new, ready, running, waiting, halted, and so on
 □ Program counter. The counter indicates the address of the next.
- □ **Program counter**. The counter indicates the address of the next instruction to be executed for this process
- □ **CPU registers**. The registers vary in number and type, depending on the computer architecture. They include accumulators, index registers, stack pointers, and general-purpose registers, plus any condition-code information
- ☐ **CPU-scheduling information**. This information includes a process priority, pointers to scheduling queues, and any other scheduling parameters
- ☐ **Memory-management information**. This information may include such items as the value of the base and limit registers and the page tables, or the segment tables





Process Scheduling

- □ The objective of multiprogramming is to have some process running at all times, to maximize CPU utilization
 □ The objective of time sharing is to switch the CPU among processes so frequently that users can interact with each program
 □ The process scheduler selects an available process (possibly from a set of several available processes) for program execution on the CPU
 □ Scheduling Queues
 □ As processes enter the system, they are put into a job queue, which consists of all processes in the system
 □ The processes that are residing in main memory and are ready and waiting to execute are kept on a list called the ready queue stored as a linked list. A ready-queue header contains pointers to the first and final PCBs in the list
 □ The list of processes weiting for a particular I/O device is called as
- ☐ The list of processes waiting for a particular I/O device is called a **device queue** each device has its own device queue




Figure 3.6 Queueing-diagram representation of process scheduling.

☐ A new process is initially put in the ready queue. It waits there until it is selected for execution, or **dispatched**

☐ The process could issue an I/O request and then be placed in an I/O queue

☐ The process could create a new child process and wait for the child's
termination
☐ The process could be removed forcibly from the CPU, as a result of
an interrupt, and be put back in the ready queue
Schedulers
☐ A process migrates among the various scheduling queues throughout
its lifetime
☐ The operating system must select, for scheduling purposes,
processes from these queues in some fashion. The selection process
is carried out by the appropriate scheduler
☐ The long-term scheduler, or job scheduler, selects processes
from this pool and loads them into memory for execution
☐ The long-term scheduler executes much less frequently;
minutes may separate the creation of one new process and the
next - controls the degree of multiprogramming
☐ An I/O-bound process is one that spends more of its time doing
I/O than it spends doing computations
☐ A CPU-bound process, in contrast, generates I/O requests
infrequently
☐ The long-term scheduler select a good process mix of
I/O-bound and CPU-bound processes
☐ The short-term scheduler , or CPU scheduler , selects from among
the processes that are ready to execute and allocates the CPU to one
of them
☐ The short-term scheduler must select a new process for the
CPU frequently. A process may execute for only a few
milliseconds before waiting for an I/O request.
☐ Some operating systems, such as time-sharing systems, may
introduce an additional, intermediate level of scheduling -
medium-term scheduler
☐ The key idea behind a medium-term scheduler is that sometimes it
can be advantageous to remove a process from memory (and from
active contention for the CPU) - reduce the degree of
multiprogramming

☐ Later, the process can be reintroduced into memory, and its execution can be continued where it left off. This scheme is called **swapping**




Figure 3.7 Addition of medium-term scheduling to the queueing diagram.

□ Context Switch □ When an interrupt occurs, the system needs to save the current context of the process running on the CPU so that it can restore that context when its processing is done □ The context is represented in the PCB of the process □ Switching the CPU to another process requires performing a state save of the current process and a state restore of a different process. This task is known as a context switch

☐ When a context switch occurs, the kernel saves the context of the old process in its PCB and loads the saved context of the new process scheduled to run

Operations on Processes

forming a tree of processes.

$\hfill\square$ The processes in most systems can execute concurrently, and they
may be created and deleted dynamically
□ Process Creation
□ a process may create several new processes
☐ the creating process is called a parent process
☐ The new processes are called the children of that process
☐ Each of these new processes may in turn create other processes.

identify processes according to a unique process identifier (or pid)




Figure 3.8 A tree of processes on a typical Linux system.

 \Box ☐ The init process (which always has a pid of 1) serves as the root parent process for all user processes. ☐ Once the system has booted, the init process can also create various user processes, such as a web or print server, an ssh server, and the like. □ two children of init—kthreadd and sshd. The kthreadd process is responsible for creating additional processes that perform tasks on behalf of the kernel (in this situation, khelper and pdflush) ☐ The sshd process is responsible for managing clients that connect to the system by using ssh ☐ The login process is responsible for managing clients that directly log onto the system □ when a process creates a child process, that child process will need resources (CPU time, memory, files, I/O devices) to accomplish its task. ☐ A child process may be able to obtain its resources directly from the

operating system, or it may be constrained to a subset of the

resources of the parent process

	the parent process may pass along initialization data (input) to the child process
	When a process creates a new process, two possibilities for
	execution exist:
	☐ 1. The parent continues to execute concurrently with its children
	have terminated
	 2. The parent waits until some or all of its children have terminated
	There are also two address-space possibilities for the new process:
	☐ 1. The child process is a duplicate of the parent process (it has
	the same program and data as the parent
	☐ 2. The child process has a new program loaded into it
П	A new process is created by the fork() system call. The new process
_	consists of a copy of the address space of the original process. This
	mechanism allows the parent process to communicate easily with its
	child process
	The return code for the fork() is zero for the new (child) process,
	whereas the (nonzero) process identifier of the child is returned to the
	parent. After a fork() system call, one of the two two processes
	typically uses the exec() system call to replace the process's memory
	space with a new program. The exec() system call loads a binary file
	into memo

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
pid_t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
   else if (pid == 0) { /* child process */
      execlp("/bin/ls","ls",NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait(NULL);
     printf("Child Complete");
   return 0;
```

Figure 3.9 Creating a separate process using the UNIX fork() system call.

Process Termination
A process terminates when it finishes executing its final statement
asks the operating system to delete it by using the exit() system call.
All the resources of the process—including physical and virtual
memory, open files, and I/O buffers—are deallocated by the operating
system.
A parent may terminate the execution of one of its children for a
variety of reasons, such as these:
The child has exceeded its usage of some of the resources that it has
been allocated.
The task assigned to the child is no longer required.
The parent is exiting, and the operating system does not allow a child
to continue if its parent terminates

☐ if a process terminates (either normally or abnormally), thenall its children must also be terminated. This phenomenon, referred to as cascading termination.
☐ A parent process may wait for the termination of a child process by using the wait() system call
The wait() system call is passed a parameter that allows the parent to obtain the exit status of the child
□ pid_t pid;
□ int status;
□ pid = wait(&status);
☐ A process that has terminated, but whose parent has not yet called wait(), is known as a zombie process.
☐ In this case, child processes are known as orphans
CPU scheduling
☐ Several processes are kept in memory at one time.
☐ By switching the CPU among processes, the operating system can make the computer more productive.
☐ CPU –I/O Burst Cycle





Figure 6.1 Alternating sequence of CPU and I/O bursts.


Whenever the CPU becomes idle, the operating system must select one of the processes in the ready queue to be executed. The selection process is carried out by the short-term scheduler, or CPU scheduler.
 CPU-scheduling decisions may take place under the following four

circumstances:

☐ 1. When a process switches from the running state to the waiting state (for example, as the result of an I/O request or an invocation of wait() for the termination of a child process)
☐ 2. When a process switches from the running state to the ready state (for example, when an interrupt occurs)
☐ 3. When a process switches from the waiting state to the ready state (for example, at completion of I/O)
☐ 4.When a process terminate
☐ When scheduling takes place only under circumstances 1 and 4, we say that the scheduling scheme is nonpreemptive or cooperative.
☐ Otherwise,it is preemptive
☐ Under nonpreemptive scheduling , once the CPU has been allocated to a process, the process keeps the CPU until it releases it either by terminating or by switching to the waiting state.
☐ Virtually all modern operating systems including Windows, macOS,
Linux, and UNIX use preemptive scheduling algorithms.
□ Dispatcher
☐ is the module that gives control of the CPU's core to the process
selected by the CPU scheduler.
☐ involves the following:
☐ Switching context from one process to another
☐ Switching to user mode
☐ Jumping to the proper location in the user program to resume
that program
□ Scheduling Criteria
$\hfill\square$ 1. CPU utilization - We want to keep the CPU as busy as possible. In
a real system, it should range from 40 percent (for a lightly loaded system) to 90 percent (for a heavily loaded system).
$\hfill\Box$ Throughput - the number of processes that are completed per time
unit, called throughput.
$\hfill\Box$ Turnaround time - The interval from the time of submission of a
process to the time of completion is the turnaround time.
$\hfill\square$ Waiting time - Waiting time is the sum of the periods spent waiting in
the ready queue.

□ Response time - time from the submission of a request until the first response is produced.
Scheduling Algorithms
☐ First-Come First-Serve (FCFS) scheduling - Refer your Class notebook for the problems we have discussed
□ Non-Preemptive Shortest Job First Scheduling (SJF) - Refer your Class notebook for the problems we have discussed
□ Preemptive Shortest Job First Scheduling (SJF) or SRTF (Shortest Remaining Time First) - Refer your Class notebook for the problems we have discussed
□ Round Robin (RR) scheduling - Refer your Class notebook for the problems we have discussed
□ Non-Preemptive Priority Scheduling - Refer your Class notebook for the problems we have discussed
☐ Preemptive Priority Scheduling - Refer your Class notebook for the problems we have discussed
Threads
□ A thread is a basic unit of CPU utilization
□ it comprises a thread ID, a program counter (PC), a register set, and a stack.
□ It shares with other threads belonging to the same process its code section, data section, and other operating-system resources, such as open files and signals.
☐ A traditional process has a single thread of control.
□ If a process has multiple threads of control, it can perform more than one task at a time.





single-threaded process

multithreaded process

Figure 4.1 Single-threaded and multithreaded processes.

■ Multithreading Models

☐ User threads are supported above the kernel and are managed without kernel support




Figure 4.6 User and kernel threads.

□ kernel threads are supported and managed directly by the operating system.

☐ 1. Many-to-One Model




Figure 4.7 Many-to-one model.

maps many user-level threads to one kernel thread.
 Thread management is done by the thread library in user space
 the entire process will block if a thread makes a blocking system call.
 one thread can access the kernel at a time, multiple threads are unable to run in parallel on multicore systems.

☐ 2. One-to-One Model




Figure 4.8 One-to-one model.

maps each user thread to a kernel thread.
 provides more concurrency than the many-to-one model by allowing another thread to run when a thread makes a blocking system call.
 allows multiple threads to run in parallel on multiprocessors.

☐ The only drawback to this model is that creating a user thread requires creating the corresponding kernel thread, and a large number of kernel threads may burden the performance of a system.

☐ 3. Many-to-Many Model




Figure 4.9 Many-to-many model.

- ☐ multiplexes many user-level threads to a smaller or equal number of kernel threads.
- ☐ The number of kernel threads may be specific to either a particular application or a particular machine

☐ Two-level model





Figure 4.10 Two-level model.

- $\hfill\Box$ One variation on the many-to-many model
- □ still multiplexes many user-level threads to a smaller or equal number of kernel threads

□ but also allows a user-level thread to be bound to a kernel thread.
Process Synchronization
☐ A system typically consists of several threads running either concurrently or in parallel.
 □ Threads often share user data □ A race condition exists when access to shared data is not controlled, possibly resulting in corrupt data values.
 □ Process synchronization involves using tools that control access to shared data to avoid race conditions.
 □ A cooperating process □ is one that can affect or be affected by other processes executing in the system
☐ Cooperating processes can either directly share a logical address space (that is, both code and data) or
☐ be allowed to share data only through shared memory or message passing
The Critical-Section Problem
 □ Consider a system consisting of n processes {P0, P1,, Pn-1}. □ Each process has a segment of code, called a critical section, in which the process may be accessing — and updating — data that is shared with at least one other process
The important feature of the system is that, when one process is executing in its critical section, no other process is allowed to execute in its critical section
 □ Each process must request permission to enter its critical section. The section of code implementing this request is the entry section. □ The critical section may be followed by an exit section
$\hfill\Box$ The remaining code is the remainder section.

```
while (true) {
     entry section
         critical section
     exit section
         remainder section
```

Figure 6.1 General structure of a typical process.



Software based solution
Peterson's solution is restricted to two processes that alternate
execution between their critical sections and remainder sections.
Peterson's solution requires the two processes to share two data
items: int turn: boolean flag[2]:

```
while (true) {
   flag[i] = true;
   turn = j;
   while (flag[j] && turn == j)
   ;

   /* critical section */

   flag[i] = false;

   /*remainder section */
}
```

Figure 6.3 The structure of process P_i in Peterson's solution.

Mutex Locks

software tool to solve the critical-section problem
We use the mutex lock to protect critical sections and thus prevent
race conditions
a process must acquire the lock before entering a critical section(
acquire()function)
it releases the lock when it exits the critical section(release()function)
A mutex lock has a boolean variable available whose value indicates
if the lock is available or not
If the lock is available, a call to acquire()succeeds, and the lock is
then considered unavailable
A process that attempts to acquire an unavailable lock is blocked until
the lock is released.

```
while (true) {
                                    acquire lock
                                        critical section
                                    release lock
                                       remainder section
               Figure 6.10 Solution to the critical-section problem using mutex locks.
The definition of acquire() is as follows:
                          acquire() {
                              while (!available)
                                 ; /* busy wait */
                              available = false;
      The definition of release() is as follows:
                          release() {
                             available = true;
☐ Calls to either acquire() or release() must be performed atomically
\hfill \square A lock is considered contended if a thread blocks while trying to
   acquire the lock
☐ If a lock is available when a thread attempts to acquire it, the lock is
   considered uncontended
□ Disadvantage
      □ busy waiting - While a process is in its critical section, any
         other process that tries to enter its critical section must loop
         continuously in the call to acquire()
☐ The type of mutex lock we have been describing is also called a spin
   lock because the process "spins" while waiting for the lock to become
   available
```

Semaphores

Ш	A semaphore 5 is an integer variable that,
	It can be initialized
	accessed only through two standard atomic operations: wait() and signal()
	definition of wait()
	<pre>wait(S) {</pre>
	while (S \leq 0)
	; // busy wait
	S;
	}
	definition of signal()
	definition of signal()
	signal(S) {
	S++;
	}
	when one process modifies the semaphore value, no other process can simultaneously
	modify that same semaphore value.
	In the case of wait(S), the testing of the integer value of S (S \leq 0), as well as its possible
	modification (S), must be executed without interruption.
Ш	The Wait Operation is used for deciding the condition for the process to enter the
	critical state or wait for execution of process
	If the Semaphore value is equal to zero then the Process has to wait for the
	Process to exit the Critical Section Area
Ш	if the Semaphore value is greater than zero or positive then the Process can enter
	the Critical Section Area
Ш	Types of Semaphores
	Counting Semaphores
	These are integer value semaphores and have an unrestricted value
	domain. These semaphores are used to coordinate the resource access,
	where the semaphore count is the number of available resources. If the
	resources are added, semaphore count automatically incremented and if
	the resources are removed, the count is decremented
	Binary Semaphores
	The binary semaphores are like counting semaphores but their value is
	restricted to 0 and 1. The wait operation only works when the semaphore

is 1 and the signal operation succeeds when semaphore is 0. It is sometimes easier to implement binary semaphores than counting semaphores □ Advantages of Semaphores ☐ Semaphores allow only one process into the critical section. They follow the mutual exclusion principle strictly and are much more efficient than some other methods of synchronization. ☐ There is no resource wastage because of busy waiting in semaphores as processor time is not wasted unnecessarily to check if a condition is fulfilled to allow a process to access the critical section. ☐ Semaphores are implemented in the machine independent code of the microkernel. So they are machine independent ■ **Example**, consider two concurrently running processes: we require that S2 be executed only after S1 has completed. ☐ We can implement this scheme readily by letting P1 and P2 share a common semaphore synch, initialized to 0. ☐ In process P1, we insert the statements S_1 ; signal(synch); ☐ In process P2, we insert the statements wait(synch); S_2 ; ☐ To **overcome the problem of busy waiting**, we can modify the definition of the wait() and signal() operations as follows: ☐ When a process executes the wait() operation and finds that the semaphore value is not positive, it must wait. However, rather than engaging in busy waiting, the process can suspend itself ☐ The suspend operation places a process into a waiting queue associated with the semaphore, and the state of the process is switched to the waiting state ☐ Then control is transferred to the CPU scheduler, which selects another process to execute

```
☐ We define a semaphore as follows:
          typedef struct {
               int value;
               struct process *list;
          } semaphore;
   ☐ Each semaphore has an integer value and a list of processes list.
   ☐ A signal() operation removes one process from the list of waiting processes
   ■ wait() semaphore operation
          wait(semaphore *S) {
                      S->value--;
                      if (S->value < 0) {
                              add this process to S->list;
                              sleep();

☐ signal() semaphore operation

             signal(semaphore *S) {
                    S->value++;
                    if (S->value <= 0) {
                           remove a process P from S->list;
                           wakeup(P);
                    }
             }
Monitors
   ☐ Suppose that a program interchanges the order in which the wait() and signal()
      operations on the semaphore mutex are executed, resulting in the following
      execution
         signal(mutex);
           critical section
         wait(mutex);
   ☐ In this situation, several processes may be executing in their critical sections
      simultaneously, violating the mutual-exclusion requirement.
   ☐ This error may be discovered only if several processes are simultaneously active
      in their critical sections
   ☐ Suppose that a program replaces signal(mutex) with wait(mutex). That is, it
      executes
```

```
wait(mutex);
...
critical section
...
wait(mutex);

In this case, the process will permanently block on the second call to wait(), as the semaphore is now unavailable
These examples illustrate that various types of errors can be generated easily when programmers use semaphores or mutex locks incorrectly to solve the critical-section problem
A monitor type is an ADT that includes a set of programmer-defined operations that are provided with mutual exclusion within the monitor
```

Figure 6.11 Pseudocode syntax of a monitor.

Ш	
	a function defined within a monitor can access only those variables declared
	locally within the monitor and its formal parameters
	Similarly, the local variables of a monitor can be accessed by only the local
	functions

☐ The monitor construct ensures that only one process at a time is active within the monitor.
☐ A programmer who needs to write a tailor-made synchronization scheme can define one or more variables of type condition: condition x, y; The only operations that can be invoked on a condition variable are wait() and signal(). The operation
x.wait();
means that the process invoking this operation is suspended until another process invokes
x.signal();
shared data operations initialization code
Figure 6.12 Schematic view of a monitor.
assic Problems of Synchronization Bounded-Buffer problem

Cla

Ш	A producer process produces information that is consumed by a consumer
	process
	For example, a compiler may produce assembly code that is consumed by an assembler
	The assembler, in turn, may produce object modules that are consumed by the loader

	One solution to the producer-consumer problem uses shared memory
	To allow producer and consumer processes to run concurrently, we must have
	available a buffer of items that can be filled by the producer and emptied by the
	consumer
	This buffer will reside in a region of memory that is shared by the producer and
	consumer processes.
	A producer can produce one item while the consumer is consuming another item
	The producer and consumer must be synchronized, so that the consumer does
	not try to consume an item that has not yet been produced
	Two types of buffers can be used
	\square The unbounded buffer places no practical limit on the size of the buffer.
	The consumer may have to wait for new items, but the producer can
	always produce new items
	$\ \square$ The bounded buffer assumes a fixed buffer size. In this case, the
	consumer must wait if the buffer is empty, and the producer must wait if
	the buffer is full
	The producer and consumer processes share the following data structures:
	int n;
	semaphore mutex = 1; semaphore empty = n;
	semaphore full = 0
Ш	We assume that the pool consists of n buffers, each capable of holding one
	item.
Ш	The mutex binary semaphore provides mutual exclusion for accesses to the
	buffer pool and is initialized to the value 1
	The empty and full semaphores count the number of empty and full buffers
	The semaphore empty is initialized to the value n
	The semaphore full is initialized to the value 0.

□ Producer Process

Figure 7.1 The structure of the producer process.

□ Consumer Process

 \Box

Figure 7.2 The structure of the consumer process.

The Readers -Writers Problem

Suppose that a database is to be shared among several concurrent processes
Some of these processes may want only to read the database (readers)
Others may want to update (that is, to read and write) the database.(writers)
if two readers access the shared data simultaneously, no adverse effects will
result.

if a writer and some other process (either a reader or a writer) access the
database simultaneously, chaos may occur
To ensure that these difficulties do not arise, we require that the writers have
exclusive access to the shared database while writing to the database.
This synchronization problem is referred to as the readers-writers problem.
Variations
first readers-writers problem
requires that no reader be kept waiting unless a writer has already obtained permission to use the shared object.
The second readers -writers problem requires
if a writer is waiting to access the object, no new readers may start reading.
A solution to either problem may result in starvation . In the first case, writers may
starve; in the second case, readers may starve.
In the solution to the first readers-writers problem, the reader processes share
the following data structures:
semaphore rw_mutex = 1;
semaphore mutex = 1;
<pre>int read_count = 0;</pre>
The semaphores mutex and rw mutex are initialized to 1; read count is initialized
to 0. The semaphore rw mutex is common to both reader and writer processes.
do {
<pre>wait(rw_mutex);</pre>
/* writing is performed */
,
signal(rw_mutex);
} while (true);
Figure 5.11 The structure of a writer process

Figure 5.12 The structure of a reader process.

☐ The Dining-Philosophers Problem

- ☐ Consider five philosophers who spend their lives thinking and eating.
- ☐ The philosophers share a circular table surrounded by five chairs, each belonging to one philosopher.




Figure 5.13 The situation of the dining philosophers.

- ☐ In the center of the table is a bowl of rice, and the table is laid with five single chopsticks
- ☐ When a philosopher thinks, she does not interact with her colleagues.
- ☐ A philosopher may pick up only one chopstick at a time.

She cannot pick up a chopstick that is already in the hand of a neighbor.
When a hungry philosopher has both her chopsticks at the same time, she eats without releasing the chopsticks.
When she is finished eating, she puts down both chopsticks and starts thinking again.
It is an example of a large class of concurrency-control problems.
It is a simple representation of the need to allocate several resources among several processes in a deadlock-free and starvation-free manner.
Solution:
One simple solution is to represent each chopstick with a semaphore.
A philosopher tries to grab a chopstick by executing a wait() operation on that semaphore.
She releases her chopsticks by executing the signal() operation on the appropriate semaphores.
The shared data are semaphore chopstick[5];
5.8
<pre>do { wait(chopstick[i]); wait(chopstick[(i+1) % 5]);</pre>
/* eat for awhile */
<pre>signal(chopstick[i]); signal(chopstick[(i+1) % 5]);</pre>
/* think for awhile */
<pre>} while (true);</pre>
Figure 5.14 The structure of philosopher i.
Although this solution guarantees that no two neighbors are eating simultaneously, it nevertheless must be rejected because it could create a deadlock.
Suppose that all five philosophers become hungry at the same time and each grabs her left chopstick. All the elements of chopstick will now be equal to 0. When each philosopher tries to grab her right chopstick, she will be delayed forever.
Several possible remedies to the deadlock problem are replaced by:

	 Allow at most four philosophers to be sitting simultaneously at the table. Allow a philosopher to pick up her chopsticks only if both chopsticks are available (to do this, she must pick them up in a critical section).
	Deadlocks
	In a multiprogramming environment, several processes may compete for a finite number of resources. A process requests resources; if the resources are not available at that time, the process enters a waiting state. Sometimes, a waiting process is never again able to change state, because the resources it has requested are held by other waiting processes. This situation is called a deadlock.
	The resources may be partitioned into several types (or classes), each consisting of some number of identical instances. CPU cycles, files, and I/O devices (such as printers and DVD drives) are examples of resource types. If a system has two CPUs, then the resource type CPU has two instances. Similarly, the resource type printer may have five instances.
	A process must request a resource before using it and must release the resource after using it.
	A process may utilize a resource in only the following sequence:
	1. Request. The process requests the resource. If the request cannot be granted immediately (for example, if the resource is being used by another process), then the requesting process must wait until it can acquire the resource.
	 2. Use. The process can operate on the resource (for example, if the resource is a printer, the process can print on the printer).
	☐ 3. Release. The process releases the resource.
	•
ш	A deadlock situation can arise if the following four conditions hold simultaneously in a system:
	☐ 1. Mutual exclusion. At least one resource must be held in a non-sharable
	mode; that is, only one process at a time can use the resource. If another process requests that resource, the requesting process must be delayed until the resource has been released.

 2. Hold and wait. A process must be holding at least one resource and waiting to acquire additional resources that are currently being held by other processes.
3. No preemption. Resources cannot be preempted; that is, a resource can be released only voluntarily by the process holding it, after that process has completed its task.
□ 4. Circular wait. A set {P0, P1,, Pn} of waiting processes must exist such that P0 is waiting for a resource held by P1, P1 is waiting for a resource held by P2,, Pn-1 is waiting for a resource held by Pn, and Pn is waiting for a resource held by P0.
Resource-Allocation Graph
Deadlocks can be described more precisely in terms of a directed graph called a
system resource-allocation graph.
This graph consists of a set of vertices V and a set of edges E.
The set of vertices V is partitioned into two different types of nodes: $P = \{P1, P2,, Pn\}$, the set consisting of all the active processes in the system, and $R = \{R1, R2,, Rm\}$, the set consisting of all resource types in the system.
A directed edge from process Pih to resource type Rj is denoted by Pi \rightarrow Rj; it signifies that process Pi has requested an instance of resource type Rj and is currently waiting for that resource. (Request edge)
A directed edge from resource type Rj to process Pi is denoted by Rj \rightarrow Pi ; it
signifies that an instance of resource type Rj has been allocated to process Pi
(Assignment edge)
Pictorially, we represent each process Pi as a circle and each resource type Rj as a rectangle.





Figure 7.1 Resource-allocation graph.

an instance of resource type R1.



- ☐ Process P2 is holding an instance of R1 and an instance of R2 and is waiting for an instance of R3.
- ☐ Process P3 is holding an instance of R3.
- ☐ If the graph contains **no cycles**, then no process in the system is deadlocked. If the graph does contain a cycle, then a deadlock may exist.




Figure 7.2 Resource-allocation graph with a deadlock.

□ Suppose that process P3 requests an instance of resource, type R2. Since no resource instance is currently available, we add a request edge P3 \rightarrow R2 to the graph (Figure 7.2). At this point, two minimal cycles exist in the system:

$$\begin{tabular}{|c|c|c|c|c|}\hline & P1 \rightarrow R1 \rightarrow P2 \rightarrow R3 \rightarrow P3 \rightarrow R2 \rightarrow P1\\ \hline \end{tabular}$$

$$\square$$
 P2 \rightarrow R3 \rightarrow P3 \rightarrow R2 \rightarrow P2

□ Processes P1, P2, and P3 are deadlocked. Process P2 is waiting for the resource R3, which is held by process P3. Process P3 is waiting for either process P1 or process P2 to release resource R2. In addition, process P1 is waiting for process P2 to release resource R1.




Figure 7.3 Resource-allocation graph with a cycle but no deadlock. ☐ Methods for Handling Deadlocks ☐ We can deal with the deadlock problem in one of three ways: □ 1. We can use a protocol to **prevent or avoid deadlocks**, ensuring that the system will never enter a deadlocked state. ☐ 2. We can allow the system to enter a deadlocked state, detect it, and recover. ☐ 3. We can ignore the problem altogether and pretend that deadlocks never occur in the system. ☐ The third solution is the one used by most operating systems, including Linux and Windows. It is then up to the application developer to write programs that handle deadlocks. ☐ Deadlock Prevention ☐ For a deadlock to occur, each of the four necessary conditions must hold. ☐ By ensuring that at least one of these conditions cannot hold, we can prevent the occurrence of a deadlock. □ 1. Mutual Exclusion ☐ The mutual exclusion condition must hold. ☐ That is, at least one resource **must be non sharable**.

\square Read-only files are a good example of a sharable resource. If
several processes attempt to open a read-only file at the
same time, they can be granted simultaneous access to the
file.
☐ 2. Hold and Wait
\square we must guarantee that, whenever a process requests a
resource, it does not hold any other resources.
\square One protocol that we can use requires each process to
request and be allocated all its resources before it begins
execution.
\square An alternative protocol allows a process to request
resources only when it has none.
☐ Both these protocols have two main disadvantages.
☐ First, resource utilization may be low, since resources
may be allocated but unused for a long period.
☐ Second, starvation is possible. A process that needs
several popular resources may have to wait indefinitely,
☐ 3. No Preemption
☐ The third necessary condition for deadlocks is that there be
no preemption of resources that have already been
allocated.
☐ We can use the following protocol:
☐ 1. If a process is holding some resources and requests
another resource that cannot be immediately allocated
to it (that is, the process must wait), then all resources
the process is currently holding are preempted.
\[\subseteq 2. Alternatively, if a process requests some resources, \]
we first check whether they are available. If they are, we allocate them. If they are not, we check whether they
anocate them. If they are not, we check whether they

are allocated to some other process that is waiting for additional resources. If so, we preempt the desired resources from the waiting process and allocate them to the requesting process. If the resources are neither available nor held by a waiting process, the requesting process must wait.

☐ 4. Circular Wait
\square One way to ensure that this condition never holds is to
impose a total ordering of all resource types and to require
that each process requests resources in an increasing order
of enumeration.
\square we let R = {R1, R2,, Rm} be the set of resource types. We
assign to each resource type a unique integer number, which
allows us to compare two resources and to determine
whether one precedes another in our ordering.
\square We define a one-to-one function F: R \rightarrow N, where N is the set
of natural numbers.
☐ function F might be defined as follows:
☐ F(tape drive) = 1
☐ F(disk drive) = 5
☐ F(printer) = 12
☐ A process can initially request any number of instances of a
resource type —say, Ri . After that, the process can request
instances of resource type Rj if and only if $F(Rj) > F(Ri)$.
□ Deadlock Avoidance
☐ prevent deadlocks by limiting how requests can be made.
☐ The simplest and most useful model requires

☐ that each process declare the maximum number of
resources of each type that it may need.
☐ that ensures that the system will never enter a deadlocked state.
☐ Safe State
☐ A state is safe if the system can allocate resources to each process (up to its maximum) in some order and still avoid a
deadlock.
☐ A system is in a safe state only if there exists a safe sequence.
☐ A sequence of processes
□ <p1, p2,,="" pn=""> is a safe sequence for the current allocation state if, for each Pi, the resource requests that Pi can still make can be satisfied by the currently available resources plus the resources held by all Pj, with j < i. </p1,>
☐ An unsafe state may lead to a deadlock.
☐ Resource-Allocation-Graph Algorithm
☐ In addition to the request and assignment edges already described, we introduce a new type of edge, called a claim edge.
\square A claim edge Pi \rightarrow Rj indicates that process Pi may request resource Rj at some time in the future. This edge resembles a request edge in direction but is represented in the graph by a dashed line.
\square When process Pi requests resource Rj , the claim edge Pi \rightarrow Rj is converted to a request edge. Similarly, when a resource Rj is released by Pi , the Assignment edge Rj \rightarrow Pi is reconverted to a claim edge Pi \rightarrow Rj .

- □ Note that the resources must be claimed a priori in the system. That is, before process Pi starts executing, all its claim edges must already appear in the resource-allocation graph.
- \square suppose that process Pi requests resource Rj . The request can be granted only if converting the request edge Pi \rightarrow Rj to an assignment edge Rj \rightarrow Pi does not result in the formation of a cycle in the resource-allocation graph.
- ☐ If no cycle exists, then the allocation of the resource will leave the system in a safe state. If a cycle is found, then the allocation will put the system in an unsafe state.




Figure 8.9 Resource-allocation graph for deadlock avoidance.

□ To illustrate this algorithm, we consider the resource-allocation graph of Figure 8.9. Suppose that T2 requests R2.AlthoughR2 is currently free, we cannot allocate it to T2, since this action will create a cycle in the graph (Figure 8.10). A cycle, as mentioned, indicates that the system is in an unsafe state. If T1 requests R2,andT2 requests R1, then a deadlock will occur




Figure 8.10 An unsafe state in a resource-allocation graph.

□ Banker's	s Algorithm
	new process enters the system, it must declare the maximum of instances of each resource type that it may need.
□ This num system.	nber may not exceed the total number of resources in the
	user requests a set of resources, the system must determine the allocation of these resources will leave the system in a e.
\square If it will, t	he resources are allocated; otherwise, the process must wait
until som	ne other process releases enough resources.
□ Data stru	ictures must be maintained to implement the Banker's
algorithm	٦.
	ailable . A vector of length m indicates the number of
	hilable resources of each type. If Available[j] equals k, then k tances of resource type Rj are available.
pro	x. An n × m matrix defines the maximum demand of each cess. If Max[i][j] equals k, then process Pi may request at st k instances of resource type Rj
eac equ	ch type currently allocated to each process. If Allocation[i][j] uals k, then process Pi is currently allocated k instances of ource type Rj

If the resulting resource-allocation state is safe, the transaction is
completed, and process Pi is allocated its resources. However, if the
new state is unsafe, then Pi must wait for Requesti , and the old
resource-allocation state is restored.

☐ Example:

 \Box

	Allocation	Max	Available
	ABC	ABC	ABC
P_0	010	753	332
P_1	200	322	
P_2	302	902	
P_3	211	222	
P_4	002	433	

☐ Content of matrix need:

	Need	
	ABC	
P_0	743	
P_1	122	
P_2	600	
P_3	011	
P_4	431	

☐ We claim that the system is currently in a safe state. Indeed, the sequence <P1, P3, P4, P2, P0> satisfies the safety criteria.

□ Suppose now that process P1 requests one additional instance of resource type A and two instances of resource type C, so Request1 = (1,0,2).

□ To decide whether this request can be immediately granted, we first check that Request1 \leq Available—that is, that $(1,0,2) \leq (3,3,2)$, which is true.

☐ We then pretend that this request has been fulfilled, and we arrive at the following new state:


	Allocation	Need	Available
	ABC	ABC	ABC
P_0	010	743	230
P_1	302	020	
P_2	302	600	
P_3	211	011	
P_4	002	431	

14 002 101
We must determine whether this new system state is safe. To do so, we execute our safety algorithm and find that the sequence <p1, p0,="" p2="" p3,="" p4,=""> satisfies the safety requirement. Hence, we can</p1,>
immediately grant the request of process P1.
when the system is in this state, a request for (3,3,0) by P4 cannot be granted, since the resources are not available.
Memory Management
Contiguous Memory Allocation
The main memory must accommodate both the operating system
and the various user processes.
The memory is usually divided into two partitions:
\square one for the resident operating system and
\square one for the user processes.
We can place the operating system in either low memory or high memory.
\square The major factor affecting this decision is the location of the
interrupt vector. Since the interrupt vector is often in low
memory, programmers usually place the operating system in low memory as well.
We usually want several user processes to reside in memory at the
same time.
In contiguous memory allocation, each process is contained in a single section of memory that is contiguous to the section containing
the next process.

One of the simplest methods for allocating memory is to divide
memory into several fixed-sized partitions .
☐ Each partition may contain exactly one process.
☐ Thus, the degree of multiprogramming is bound by the number
of partitions.
\square In this multiple-partition method, when a partition is free, a
process is selected from the input queue and is loaded into the
free partition.
In the variable-partition scheme , the operating system keeps a table
indicating which parts of memory are available and which are
occupied.
Initially, all memory is available for user processes and is considered
one large block of available memory, a hole.
Eventually, as you will see, memory contains a set of holes of various
sizes.
As processes enter the system, they are put into an input queue.
When a process is allocated space, it is loaded into memory, and it
can then compete for CPU time. When a process terminates, it
releases its memory, which the operating system may then fill with
another process from the input queue.
The memory blocks available comprise a set of holes of various sizes
scattered throughout memory.
When a process arrives and needs memory, the system searches the
set for a hole that is large enough for this process.
If the hole is too large, it is split into two parts. One part is allocated
to the arriving process; the other is returned to the set of holes.
When a process terminates, it releases its block of memory, which is
then placed back in the set of holes.
,
request of size n from a list of free holes.
Solutions to this problem
First fit. Allocate the first hole that is big enough. Searching can start
either at the beginning of the set of holes or at the location where the

previous first-fit search ended. We can stop searching as soon as we
find a free hole that is large enough.
Best fit. Allocate the smallest hole that is big enough. We must
search the entire list, unless the list is ordered by size. This strategy
produces the smallest leftover hole.
Worst fit. Allocate the largest hole. Again, we must search the entire
list, unless it is sorted by size. This strategy produces the largest
leftover hole, which may be more useful than the smaller leftover hole
from a best-fit approach.
Problem discussed in class regarding first fit, best fit and worst fit strategies
Memory fragmentation can be internal as well as external.
Well as external.
Segmentation
When writing a program, a programmer thinks of it as a main
program with a set of methods, procedures, or functions.
It may also include various data structures: objects, arrays,
stacks, variables, and so on
Each of these modules or data elements is referred to by
name.
The programmer talks about "the stack," "the math library,"
and "the main program" without caring what addresses in
memory these elements occupy.
Segments vary in length, and the length of each is
intrinsically defined by its purpose in the program.
Segmentation is a memory-management scheme that
supports this programmer view of memory.
A logical address space is a collection of segments.
Each segment has a name and a length.

☐ The addresses specify both the segment name and the
offset within the segment.
\square The programmer therefore specifies each address by two
quantities: a segment name and an offset.
\square A logical address: <segment-number, offset="">.</segment-number,>
\square A C compiler might create separate segments for the
following:
□ 1. The code
☐ 2. Global variables
\square 3. The heap, from which memory is allocated
☐ 4. The stacks used by each thread
□ 5. The standard C library
☐ Libraries that are linked in during compile time might be
assigned separate segments.
\square The loader would take all these segments and assign them
segment numbers.
□ Segmentation Hardware
☐ Each entry in the segment table has a segment base and a segment limit.
☐ The segment base contains the starting physical address
where the segment resides in memory, and the segment limit
specifies the length of the segment.
☐ A logical address consists of two parts: a segment number,
s, and an offset into that segment, d.
☐ The segment number is used as an index to the segment
table
☐ The offset d of the logical address must be between 0 and
the segment limit.
-



- □ Figure 8.8 Segmentation hardware. Activate W
 □ Example of Segmentation
 □ We have five segments numbered from 0 through 4.
 □ The segment table has a separate entry for each segment, giving the beginning address of the segment in physical memory (or base) and the length of that segment (or limit).
 □ a reference to byte 53 of segment 2 is mapped onto location 4300 + 53 = 4353.
 □ A reference to segment 3, byte 852, is mapped to 3200 (the
- base of segment 3) + 852 = 4052.
- ☐ A reference to byte 1222 of segment 0 would result in a trap to the operating system, as this segment is only 1,000 bytes long.




Figure 8.9 Example of segmentation.