### Fundamentos de los Sistemas Operativos (FSO)

Departamento de Informática de Sistemas y Computadoras (DISCA) *Universitat Politècnica de València* 

Part 2: Process management

Unit 6

**Synchronization: Basic solutions** 





#### Goals

To understand the critical section concept


Synchronization: Basic solutions

- To know the mechanisms provided by the computer hardware to support synchronization
- To solve synchronization problems by means of software and hardware solutions

# Bibliography

Silberschatz, chapter 6

- The critical section problem
- Software solutions
- Hardware solutions
- Active waiting
- Exercises



#### Critical section problem

- N>1 activities (processes / threads) execute concurrently accessing (writing/reading) shared data
- Every activity
  - It has (at least) a code zone where it accesses to shared data -> This code zone is named critical section
  - It can have other code zones where there are no access to shared data ->
     These code zones are together named remaining section

#### Solution

To find a protocol to synchronize access to critical sections avoiding

race condition

Thread/process access to the critical section must be serialized

Input protocol
Critical section
Output protocol
Reamining section


# The critical section access protocol has to verify the following three conditions:

- Mutual exclusion: if an activity is inside its critical section then no other activities can be at the same time in their critical sections, the others must wait until the critical section is free
- <u>Progress:</u> if the critical section is free and there are more than one activity willing to enter it, the decision about which one enters is taken in finite time and only depends on the waiting activities
- <u>Limited waiting:</u> After an activity has asked to enter the critical section there is a limited number of times other activities are allowed entering the critical section
- It is supposed that:
  - Activities are executed at non zero speed


The critical section problem

Correctness cannot rely on the relative activity execution speed


 Critical section access protocol has to verify the following three conditions:



 Critical section access protocol has to verify the following three conditions:




 Critical section access protocol has to verify the following three conditions:



- Solutions
  - Basic
    - Software solutions
      - The protocol is implemented at user level, without added mechanisms (i.e. Decker algorithms)
    - Hardware solutions
      - Special machine instructions are used to implement the protocol
  - With OS support
    - The protocol is provided by the OS by means of system calls
  - With programming language support
    - Some programming languages (i.e. Ada95, Java) provide data types that assure automatic mutual exclusion


- The critical section problem
- Software solutions
- Hardware solutions
- Active waiting
- Exercises



#### Basic algorithm

Software solutions

Several activities use a shared variable "key" that indicates the critical section is busy, "key" is initialized to 0



It doesn't verify "mutual exclusion".
 If there is a context switch in (\*) it is possible that several threads enter the critical section

Software solutions

- Two activities synchronize by means of a global variable turn that indicates the activity turn to enter the critical section
  - turn must be initialized to I or J

Decker solution nº 1, strict alternation

```
void *thread_J(void *p) {
   while(1) {
     while (turn != J)
        /*empty loop*/;

   /* Critical section */
   turn = I;


   /* Remaining section */
}
```

- Works only with TWO threads
- It doesn't verify the "progress" condition. It imposes a "relative speed" between threads

### There exist completely correct software solutions:

- Decker, Peterson and Lamport algorithms
- Software solutions are applied in distributed systems

- The critical section problem
- Software solutions
- Hardware solutions
- Active waiting
- Exercises







- When the activities are executed in the same processor or in a shared memory multiprocessor then hardware solutions are used, like:
  - Disabling interrupts (privileged instructions)
    - Activities must run on the same processor
  - Atomic instructions to access memory (i.e. test-and-set)
    - General solution for shared memory

## **Disable interrupts**

- Execution of the following machine instructions
  - DI: disable interrupts
  - EI: enable interrupts





This is much more than required, we only need to avoid simultaneous linked critical sections

Only applicable to kernel level: DI and EI can only be executed in kernel mode

### Atomic instruction "test-and-set"

- It allows atomic evaluation and change of a variable with only one machine instruction
- "test and set" functional specification is the following:

```
int test_and_set (int *target)
{
  int aux;
    Done by
    only one
    aux = *target;
    *target = 1;
    return aux;
}
```

 It returns the actual value (1 or 0) of "target", indicating true or false, respectively; and finally it sets target to 1 (true). The operation sequence is done atomically

Atomic = Indivisible, execution cannot be interrupted


### **Atomic instruction "test-and-set"** (cont)

- Protocol to manage the critical section
  - Suppose N>1 threads executing the following code
  - Variable key is shared and initialized to 0 (false)

/\* Global variable\*/
int key=0;

- It complies with mutual exclusion and progress but it doesn't with limited waiting
  - The following thread entering the critical section is unknown

- The critical section problem
- Software solutions
- Hardware solutions
- Active waiting
- Exercises



# **Active** waiting

- All the described solutions (software and test\_and\_set) have a common feature: active waiting
- The critical section entering protocol prevents entering by forcing the execution of an empty loop that consumes CPU time

#### **ACTIVE WAITING**

```
void *thread_I(void *p) {

while(1) {
    while (turn != I)

    /* empty loop */

    /* Critical section */
    turn = J;

    /* Remaining section*/
}
```

```
void *thread_i(void *p) {

while(1) {
    while (test_and set(&key))

    /* empty loop */

    /* Critical section */
    key = 0; /*false*/
    /* Remaining section */
}
```

Software solutions ("Decker nº 1", strict alternance)


Protocol "test-and-set" atomic instruction

#### Advantage:

- Allows stopping an activity without calling the OS
- Disadvantages:

**Active** waiting

- If scheduling is based on priorities:
  - If a thread with higher priority gets cached in an active waiting while a thread with lower priority is inside the critical section, all the other threads will keep waiting forever (priority inversion)
- Even within less troubling schedule policies like round-robin:
  - Active waiting wastes processor time



# **Active** waiting

- Active waiting alternatives
  - Rely on the OS to suspend the thread that does test\_and\_set
     and can't enter the critical section

```
while( test_and_set(&key) ) {usleep(time);}
```

Or simply forcing the thread to leave the CPU

```
while( test_and_set(&key) ) {yield();}
```

 The OS provides synchronization objects where activities can keep suspended until another activity will awake them, i.e.

#### SEMAPHORES AND MUTEXES

- They are accessed through system calls synchronization primitives are provided by the OS
- No active waiting the OS can keep activities suspended efficiently avoiding CPU waste in active waiting

**Event based waiting** 

# Active waiting

- **Example**: Producer/consumer
  - Hardware solution
    - test\_and\_set , atomic instruction


```
#define N 20
int buffer[N];
int input, output, counter;
int key = 0;
```

```
void *func prod(void *p) {
  int item;
  while(1) {
    item = produce();
    while (test and set(&key))
      /*empty loop*/;
    while (counter == N)
      /*empty loop*/;
    buffer[input] = item;
    input = (input + 1) \% N;
    counter = counter + 1;
    key = 0;
```

```
void *func_cons(void *p) {
  int item;
  while(1) {
    while (test and set(&key))
      /*empty loop*/;
    while (counter == 0)
      /*empty loop*/;
    item = buffer[output];
    output = (output + 1) % N;
    counter = counter - 1;
    key = 0;
    consume(item);
```

- There are problems in this code and it doesn't work
  - ¿Where are the problems?

- The critical section problem
- Software solutions
- Hardware solutions
- Active waiting
- Exercises



#### **Exercise 6.1:**

Describe if the following code is a good solution to the critical section problem when there are only two threads involved

(thread\_0 and thread\_1)

```
#include <stdio.h>
/** Shared **/
int flag[2];
```

```
thread_i(void) {
 while ( 1 ) {
   remaining_section;
    flag[i] = 1;
    while(flag[(i+1) % 2]);
    critical_section;
    flag[i] = 0;
```

¿Does it comply with the three critical section protocol conditions?

#### **Exercise 6.2:**

Exercises

Compare the three test-and-set based proposed solutions to the critical section problem

```
/* Solution a */
void *thread(void *p) {

  while(1) {
    while (test_and_set(&key));
    /* Critical section */
    key = 0;
    /* Remaining section */
}
```

```
/* Solution b */
void *thread(void *p) {

while(1) {
 while (test_and_set(&key)) usleep(1000);
   /* Critical section */
   key = 0;
   /* Remaining section */
}
```

```
#include <stdio.h>
/** Shared **/
int key=0;
```

```
/* Solution c*/
void *thread(void *p) {

while(1) {
 while (test_and_set(&key)) yield();
   /* Critical section */
   key = 0;
   /* Remaining section */
}
```

**Note. yield()** call allows leaving the remaining CPU time to others. In this way the thread that calls to yield() goes to READY and frees the CPU, and gives the scheduler the opportunity to select another activity for execution

#### **Exercise 6.3:**

**Exercises** 

The following functions are executed by two concurrent threads inside the same process. Indicate what shared resources appear in the code and what mechanisms are used to avoid race conditions.

```
void *add (void *argument)
                                          void *subtract (void *argument)
  int ct, tmp;
                                            int ct, tmp;
  for (ct=0;ct<REPE;ct++)</pre>
                                            for (ct=0;ct<REPE;ct++)</pre>
     while (test and set (\&key) == 1);
                                                while (test and set (&key) == 1);
     tmp = V;
                                                tmp = V;
     tmp++;
                                                tmp--;
     V = tmp;
                                                V = tmp;
     key = 0;
                                                key = 0;
  printf("->ADD (V=%ld) \n", V);
  pthread exit(0);
                                           printf("->SUBSTRACT (V=%ld)\n", V);
                                            pthread exit(0);
```

**Note**. The variables and functions not defined inside functions add and subtract are defined as global