STAT 423/523 Statistical Methods for Engineers and Scientists

Lecture 10: Simple Linear Regression

Chencheng Cai

Washington State University

Simple Linear Regression

Regression is a statistical method for estimating the relationships among variables. THe simpest form of regression is **simple linear regression**:

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

Simple Linear Regression


Regression is a statistical method for estimating the relationships among variables. THe simpest form of regression is **simple linear regression**:

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

- \triangleright y_i is the response variable (dependent variable).
- $ightharpoonup x_i$ is the predictor variable (independent variable).
- \triangleright β_0 is the intercept.
- \triangleright β_1 is the slope.
- $ightharpoonup \epsilon_i$ is the error term.

Example

- ightharpoonup y: ocular surface area
- ▶ x: width of the palprebal fissure



Assumptions

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

- ightharpoonup Linearity: The relationship between x and y is linear.
- Independence: The errors are independent.
- Normality: The errors are normally distributed.
- **Equal variance:** The errors have constant variance.

Assumptions

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

- ightharpoonup Linearity: The relationship between x and y is linear.
- Independence: The errors are independent.
- Normality: The errors are normally distributed.
- **Equal variance**: The errors have constant variance.

For short, the LINE assumptions give:

$$y_i = \beta_0 + \beta_1 x_i + N(0, \sigma^2) \quad \forall i$$

Violations of Assumptions

- Linearity: Nonliear regression model.
- ▶ Independence: Structural equation model (SEM) in econometrics.
- Normality: ϵ_i could have a heavy-tailed distribution.
- ► Equal variance: Heteroscedasticity.

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

We assume all x_i 's are fixed and known. (not random variables!)

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

We assume all x_i 's are fixed and known. (not random variables!)

 $ightharpoonup E(y_i) = \beta_0 + \beta_1 x_i$ is the mean response for a given x_i .

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

We assume all x_i 's are fixed and known. (not random variables!)

- $ightharpoonup E(y_i) = \beta_0 + \beta_1 x_i$ is the mean response for a given x_i .
- $Var(y_i) = Var(\epsilon_i) = \sigma^2$ is the variance of the response.

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

We assume all x_i 's are fixed and known. (not random variables!)

- $ightharpoonup E(y_i) = \beta_0 + \beta_1 x_i$ is the mean response for a given x_i .
- $Var(y_i) = Var(\epsilon_i) = \sigma^2$ is the variance of the response.
- $ightharpoonup Cov(y_i,y_j)=Cov(\epsilon_i,\epsilon_j)$ for $i\neq j$. (Independence Assumption).

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

We assume all x_i 's are fixed and known. (not random variables!)

- $ightharpoonup E(y_i) = \beta_0 + \beta_1 x_i$ is the mean response for a given x_i .
- $Var(y_i) = Var(\epsilon_i) = \sigma^2$ is the variance of the response.
- $ightharpoonup Cov(y_i,y_j)=Cov(\epsilon_i,\epsilon_j)$ for $i\neq j$. (Independence Assumption).

If we get the estimated coefficients $\hat{\beta}_0$ and $\hat{\beta}_1$,

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

We assume all x_i 's are fixed and known. (not random variables!)

- $ightharpoonup E(y_i) = \beta_0 + \beta_1 x_i$ is the mean response for a given x_i .
- $ightharpoonup Var(y_i) = Var(\epsilon_i) = \sigma^2$ is the variance of the response.
- $ightharpoonup Cov(y_i,y_j)=Cov(\epsilon_i,\epsilon_j)$ for $i\neq j$. (Independence Assumption).


If we get the estimated coefficients $\hat{\beta}_0$ and $\hat{\beta}_1$,

- ► The **fitted value** for y_i is $\hat{y}_i = \hat{\beta}_0 + \hat{\beta}_1 x_i$.
- ► The **residual** for y_i is $\hat{\epsilon}_i = y_i \hat{y}_i$.

Estimation

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i.$$

Given the data points



we want to find the line that **best fits** the data points.

Ordinary Least Squares

The first approach is **Ordinary Least Squares** (OLS).

Ordinary Least Squares

The first approach is **Ordinary Least Squares** (OLS).

▶ For each possible parameter values β_0 and β_1 , we can calculate the **residual sum** of squares (RSS):

$$RSS(\beta_0, \beta_1) = \sum_{i=1}^{N} (y_i - \beta_0 - \beta_1 x_i)^2$$

Ordinary Least Squares

The first approach is **Ordinary Least Squares** (OLS).

▶ For each possible parameter values β_0 and β_1 , we can calculate the **residual sum** of squares (RSS):

$$RSS(\beta_0, \beta_1) = \sum_{i=1}^{N} (y_i - \beta_0 - \beta_1 x_i)^2$$

▶ The OLS estimates are the values of β_0 and β_1 that minimize the RSS:

$$\hat{\beta}_0, \hat{\beta}_1 = \underset{\beta_0, \beta_1}{\operatorname{arg\,min}} \operatorname{RSS}(\beta_0, \beta_1)$$

Residual Sum of Squares


The residual sum of squares is the sum of the squared distance between the data points and the fitted line.

It is the **vertical** distance, not the orthogonal distance.

Residual Sum of Squares

The residual sum of squares is the sum of the squared distance between the data points and the fitted line.

It is the vertical distance, not the orthogonal distance.





In order to minimize the RSS, we first compute its partial derivatives.

$$RSS(\beta_0, \beta_1) = \sum_{i=1}^{n} (y_i - \beta_0 - \beta_1 x_i)^2$$

$$\frac{\partial RSS}{\partial \beta_0} = -2 \sum_{i=1}^{n} (y_i - \beta_0 - \beta_1 x_i) = -2 \sum_{i=1}^{n} y_i + 2N\beta_0 + 2\beta_1 \sum_{i=1}^{n} x_i$$

$$\frac{\partial RSS}{\partial \beta_1} = -2 \sum_{i=1}^{n} (y_i - \beta_0 - \beta_1 x_i) x_i = -2 \sum_{i=1}^{n} y_i x_i + 2\beta_0 \sum_{i=1}^{n} x_i + 2\beta_1 \sum_{i=1}^{n} x_i^2$$

To find the minimum, we set the partial derivatives to zero.

The **estimating equations** for OLS are:

$$0 = -2\sum_{i=1}^{n} y_i + 2n\beta_0 + 2\beta_1 \sum_{i=1}^{n} x_i$$
 (1)

$$0 = -2\sum_{i=1}^{n} y_i x_i + 2\beta_0 \sum_{i=1}^{n} x_i + 2\beta_1 \sum_{i=1}^{n} x_i^2$$
 (2)

The **estimating equations** for OLS are:

$$0 = -2\sum_{i=1}^{n} y_i + 2n\beta_0 + 2\beta_1 \sum_{i=1}^{n} x_i$$
 (1)

$$0 = -2\sum_{i=1}^{n} y_i x_i + 2\beta_0 \sum_{i=1}^{n} x_i + 2\beta_1 \sum_{i=1}^{n} x_i^2$$
 (2)

Compute $(1) \times \sum_{i} x_i - (2) \times n$:

$$0 = 2n \sum_{i} x_{i} y_{i} - 2 \sum_{i} x_{i} \sum_{i} y_{i} + \left(\left(\sum_{i} x_{i} \right)^{2} - n \sum_{i} x_{i}^{2} \right) \beta_{1}.$$

The **estimating equations** for OLS are:

$$0 = -2\sum_{i=1}^{n} y_i + 2n\beta_0 + 2\beta_1 \sum_{i=1}^{n} x_i$$
 (1)

$$0 = -2\sum_{i=1}^{n} y_i x_i + 2\beta_0 \sum_{i=1}^{n} x_i + 2\beta_1 \sum_{i=1}^{n} x_i^2$$
 (2)

Compute $(1) \times \sum_{i} x_i - (2) \times n$:

$$0 = 2n \sum_{i} x_{i} y_{i} - 2 \sum_{i} x_{i} \sum_{i} y_{i} + \left(\left(\sum_{i} x_{i} \right)^{2} - n \sum_{i} x_{i}^{2} \right) \beta_{1}.$$

$$\Longrightarrow \hat{\beta}_{1} = \frac{\sum_{i} x_{i} y_{i} - n^{-1} \sum_{i} x_{i} \sum_{i} y_{i}}{\sum_{i} x_{i}^{2} - n^{-1} \left(\sum_{i} x_{i} \right)^{2}}.$$

$$\hat{\beta}_1 = \frac{\sum_i x_i y_i - n^{-1} \sum_i x_i \sum_i y_i}{\sum_i x_i^2 - n^{-1} \left(\sum_i x_i\right)^2}.$$

The numerator is

$$\sum_{i} x_{i} y_{i} - n^{-1} \sum_{i} x_{i} \sum_{i} y_{i} = S_{xy} = \sum_{i} (y_{i} - \bar{y})(x_{i} - \bar{x})$$

► The denominator is

$$\sum_{i} x_{i}^{2} - n^{-1} \left(\sum_{i} x_{i} \right)^{2} = S_{xx} = \sum_{i} (x_{i} - \bar{x})^{2}$$

Therefore,

$$\hat{\beta}_1 = \frac{S_{xy}}{S_{xx}} = \frac{\text{Cov}(X, Y)}{\text{Var}(X)}$$

with

$$S_{xy} = \sum_{i} (y_i - \bar{y})(x_i - \bar{x}) = \sum_{i} y_i x_i - n^{-1} \sum_{i} x_i \sum_{i} y_i$$
$$S_{xx} = \sum_{i} (x_i - \bar{x})^2 = \sum_{i} x_i^2 - n^{-1} \left(\sum_{i} x_i\right)^2$$

Therefore,

$$\hat{\beta}_1 = \frac{S_{xy}}{S_{xx}} = \frac{\text{Cov}(X, Y)}{\text{Var}(X)}$$

with

$$S_{xy} = \sum_{i} (y_i - \bar{y})(x_i - \bar{x}) = \sum_{i} y_i x_i - n^{-1} \sum_{i} x_i \sum_{i} y_i$$
$$S_{xx} = \sum_{i} (x_i - \bar{x})^2 = \sum_{i} x_i^2 - n^{-1} \left(\sum_{i} x_i\right)^2$$

From Eq. (1), we can get $\hat{\beta}_0$:

$$\hat{\beta}_0 = \bar{y} - \hat{\beta}_1 \bar{x}.$$

We still have σ^2 to estimate.

We still have σ^2 to estimate. The easiest way is to estimate it from the residual sum of squares:

$$\hat{\sigma}^2 = \frac{\text{RSS}(\hat{\beta}_0, \hat{\beta}_1)}{n-2}$$

▶ n-2 is the degrees of freedom.

We still have σ^2 to estimate. The easiest way is to estimate it from the residual sum of squares:

$$\hat{\sigma}^2 = \frac{\text{RSS}(\hat{\beta}_0, \hat{\beta}_1)}{n-2}$$

ightharpoonup n-2 is the degrees of freedom.

A quick formula in computing $\mathrm{RSS}(\hat{\beta}_0,\hat{\beta}_1)$ is

$$RSS(\hat{\beta}_0, \hat{\beta}_1) = S_{yy} - \hat{\beta}_1 S_{xy} = S_{yy} - \hat{\beta}_1^2 S_{xx},$$

where

$$S_{yy} = \sum_{i} (y_i - \bar{y})^2 = \sum_{i} y_i^2 - n^{-1} \left(\sum_{i} y_i\right)^2.$$

Summary for OLS estimators:

$$\hat{\beta}_1 = \frac{S_{xy}}{S_{xx}} = \frac{\text{Cov}(X, Y)}{\text{Var}(X)}$$

$$\hat{\beta}_0 = \bar{y} - \hat{\beta}_1 \bar{x}$$

$$\hat{\sigma}^2 = \frac{\text{RSS}(\hat{\beta}_0, \hat{\beta}_1)}{n - 2} = \frac{S_{yy} - \hat{\beta}_1 S_{xy}}{n - 2}$$

Example (Textbook Example 12.8)

x	12	30	36	40	45	57	62	67	71	78	93	94	100	105
у	3.3	3.2	3.4	3.0	2.8	2.9	2.7	2.6	2.5	2.6	2.2	2.0	2.3	2.1

Some statistics:

$$n = 14$$

$$\sum x_i = 890$$

$$\sum x_i^2 = 67182$$

$$\sum y_i = 37.6$$

$$\sum y_i^2 = 103.54$$

$$\sum x_i y_i = 2234.30$$

Example (Textbook Example 12.8)

We can compute the following statistics:

$$S_{xx} = 10603.43, \quad S_{xy} = -155.99, \quad S_{yy} = 2.557$$

The estimators are

$$\hat{\beta}_1 = \frac{S_{xy}}{S_{xx}} = \frac{-155.99}{10603.43} = -0.0147$$

$$\hat{\beta}_0 = \bar{y} - \hat{\beta}_1 \bar{x} = \frac{37.6}{14} - (-0.0147) \times \frac{890}{14} = 3.62$$

$$\hat{\sigma}^2 = \frac{S_{yy} - \hat{\beta}_1 S_{xy}}{n - 2} = \frac{2.557 - (-0.0147) \times (-155.99)}{14 - 2} = 0.022$$

▶ Because x_i 's are fixed, S_{xx} is not a random variable.

- ▶ Because x_i 's are fixed, S_{xx} is not a random variable.
- $ightharpoonup S_{xy}$ can be written as

$$S_{xy} = \sum x_i \underline{y_i} - n^{-1} \sum x_i \sum \underline{y_i} = \sum_i [(x_i - \bar{x}) \underline{y_i}]$$

The highlighted y_i 's are the only random variables and we have

$$\mathbf{y_i} \sim N(\beta_0 + \beta_1 x_i, \sigma^2),$$

where β_0 and β_1 are the true parameters.

- ▶ Because x_i 's are fixed, S_{xx} is not a random variable.
- $ightharpoonup S_{xy}$ can be written as

$$S_{xy} = \sum x_i \underline{y_i} - n^{-1} \sum x_i \sum \underline{y_i} = \sum_i [(x_i - \bar{x}) \underline{y_i}]$$

The highlighted y_i 's are the only random variables and we have

$$\mathbf{y_i} \sim N(\beta_0 + \beta_1 x_i, \sigma^2),$$

where β_0 and β_1 are the true parameters.

Therefore, S_{xy} is a linear combination of normal random variables and is also normally distributed,

$$S_{xy} \sim N(\beta_1 S_{xx}, \sigma^2 S_{xx})$$

- ▶ Because x_i 's are fixed, S_{xx} is not a random variable.
- $ightharpoonup S_{xy}$ can be written as

$$S_{xy} = \sum x_i \underline{y_i} - n^{-1} \sum x_i \sum \underline{y_i} = \sum_i [(x_i - \bar{x}) \underline{y_i}]$$

The highlighted y_i 's are the only random variables and we have

$$\mathbf{y_i} \sim N(\beta_0 + \beta_1 x_i, \sigma^2),$$

where β_0 and β_1 are the true parameters.

Therefore, S_{xy} is a linear combination of normal random variables and is also normally distributed,

$$S_{xy} \sim N(\beta_1 S_{xx}, \sigma^2 S_{xx})$$

Now we have

$$\hat{\beta}_1 = \frac{S_{xy}}{S_{xx}} \sim N(\beta_1, \sigma^2 S_{xx}^{-1})$$



► For the intercept estimator, we have

$$\hat{\beta}_0 = \bar{y} - \hat{\beta}_1 \bar{x} \sim N(\beta_0, (n^{-1} + \bar{x}^2 S_{xx}^{-1}) \sigma^2)$$

► For the intercept estimator, we have

$$\hat{\beta}_0 = \bar{y} - \hat{\beta}_1 \bar{x} \sim N(\beta_0, (n^{-1} + \bar{x}^2 S_{xx}^{-1}) \sigma^2)$$

► For the variance estimator, we have

$$E(\hat{\sigma}^2) = \sigma^2.$$

Summary:

► All OLS estimators are **unbiased**:

$$E(\hat{\beta}_0) = \beta_0$$

$$E(\hat{\beta}_1) = \beta_1$$

$$E(\hat{\sigma}^2) = \sigma^2$$

▶ The estimated **standard errors (se)** of the estimators are:

$$\widehat{se}(\hat{\beta}_0) = \sqrt{(n^{-1} + \bar{x}^2 S_{xx}^{-1}) \hat{\sigma}^2}$$

$$\widehat{se}(\hat{\beta}_1) = \sqrt{S_{xx}^{-1} \hat{\sigma}^2}$$

$$\widehat{se}(\hat{\sigma}^2) = \sqrt{\frac{2\hat{\sigma}^4}{n-2}}$$