inotify+rsync实现实时同步部署

笔记本: 剪藏

创建时间: 2019/5/14 11:24 **更新时间**: 2019/5/14 13:48

inotify+rsync实现实时同步部署

1.1.架构规划

1.1.1架构规划准备

服务器系统	角色	IP
Centos6.7 x86_64	NFS服务器端(NFS- server-inotify-tools)	192.168.1.14
Centos6.7 x86_64	rsync服务器端(rsync热备 服务器)	192.168.1.17

1.1.2架构图



2.1 部署前检查

2.1.1 检查rsync热备服务器daemon是否起来

- 1 [root@backup data]# lsof -i:873
- 2 COMMAND PID USER FD TYPE DEVICE SIZE/OFF NODE NAME
- 3 rsync 3071 root 3u IPv4 18684 0t0 TCP *:rsync (LISTEN)
- 4 rsync 3071 root 5u IPv6 18685 0t0 TCP *:rsync (LISTEN)
- 5 [root@backup data]# ps -ef|grep rsync|grep -v grep
- 6 root 3071 1 0 Dec02 ? 00:00:00 rsync --daemon
- 7 [root@backup data]#

2.1.2 NFS服务器相对于rsync服务器来说是客户端,所以要配置一个客户端密码

- 1 [root@nfs-server ~]# echo "zhurui" >>/etc/rsync.password
- 2 [root@nfs-server ~]# cat /etc/rsync.password
- 3 zhurui
- 4 [root@nfs-server ~]# chmod 600 /etc/rsync.password
- 5 [root@nfs-server ~]# II /etc/rsync.password
- 6 -rw-----. 1 root root 7 Jan 31 00:49 /etc/rsync.password
- 7 [root@nfs-server ~]#

2.1.3 NFS客户端手动推/data/目录下数据到rsync热备服务器/backup目录下

- 1 [root@nfs-server data]# showmount -e localhost ##检查共享目录
- 2 Export list for localhost:
- 3 /data 192.168.1.0/24
- 4 [root@nfs-server ~]# cd /data/
- 5 [root@nfs-server data]# II
- 6 total 12
- 7 -rw-r--r--. 1 nfsnobody nfsnobody 0 Jan 30 03:05 beautiful.txt
- 8 -rw-r--r--. 1 nfsnobody nfsnobody 9 Jan 30 04:33 f11.txt
- 9 -rw-r--r-. 1 root root 0 Jan 30 04:41 fs.txt
- 10 drwxr-xr-x. 2 nfsnobody nfsnobody 4096 Jan 30 03:05 huang

```
11 -rw-r--r-. 1 nfsnobody nfsnobody 0 Jan 30 03:17 reew.txt
```

- 12 -rw-r--r-. 1 root root 0 Jan 30 02:51 test1.txt
- 13 -rw-r--r-. 1 nfsnobody nfsnobody 0 Jan 30 04:41 wd.txt
- 14 drwxr-xr-x. 2 nfsnobody nfsnobody 4096 Jan 30 02:57 zhurui
- 15 -rw-r--r-. 1 nfsnobody nfsnobody 0 Jan 30 02:47 zhurui1.txt
- 16 -rw-r--r-. 1 nfsnobody root 0 Jan 30 02:10 zhurui.txt
- 17 [root@nfs-server /]# rsync -avz /data/ rsync_backup@192.168.1.17::backup/ --password-file=/etc/rsync.password ##推送数据命令
- 18 sending incremental file list
- 19./
- 20 beautiful.txt
- 21 f11.txt
- 22 fs.txt
- 23 reew.txt
- 24 test1.txt
- 25 wd.txt
- 26 zhurui.txt
- 27 zhurui1.txt
- 28 huang/
- 29 zhurui/
- 30
- 31 sent 572 bytes received 171 bytes 114.31 bytes/sec
- 32 total size is 9 speedup is 0.01

2.1.4 rsync服务器端检查/backup目录下数据

3.1 服务部署

3.1.1 NFS服务端安装inotify工具

inofity-tools下载地址: http://github.com/downloads/rvoicilas/inotify-tools/inotify-tools-3.14.tar.gz

1) 查看当前系统是否支持inotify

- 1 [root@nfs-server tools]# uname -r ##内核版本,从kernel2.6.13开始支持
- 2 2.6.32-573.el6.x86 64
- 3 [root@nfs-server tools]# ls -l /proc/sys/fs/inotify/ ##查看是否支持
- 4 total 0
- 5 -rw-r--r-- 1 root root 0 Jan 31 01:34 max gueued events
- 6 -rw-r--r-- 1 root root 0 Jan 31 01:34 max user instances
- 7 -rw-r--r-- 1 root root 0 Jan 31 01:34 max user watches
- 8 ##显示当前三个文件表示支持

2) 下载inotify源码包

- 1 [root@nfs-server tools]# ||
- 2 total 352
- 3 -rw-r--r--. 1 root root 358772 Mar 14 2010 inotify-tools-3.14.tar.gz

3) 编译安装inotify

- 1 [root@nfs-server tools]# tar zxf inotify-tools-3.14.tar.gz
- 2 [root@nfs-server tools]# cd inotify-tools-3.14
- 3 [root@nfs-server inotify-tools-3.14]# ./configure --prefix=/usr/local/inotify-tools-3.14
- 4 [root@nfs-server inotify-tools-3.14]# make&&make install
- 1 [root@nfs-server inotify-tools-3.14]# In -s /usr/local/inotify-tools-3.14/ /usr/local/inotify-tools ##创建软链接
- 2 [root@nfs-server inotify-tools-3.14]# cd ..
- 3 [root@nfs-server local]# II

- 4 total 44
- 5 drwxr-xr-x. 2 root root 4096 Sep 23 2011 bin
- 6 drwxr-xr-x. 2 root root 4096 Sep 23 2011 etc
- 7 drwxr-xr-x. 2 root root 4096 Sep 23 2011 games
- 8 drwxr-xr-x. 2 root root 4096 Sep 23 2011 include
- 9 Irwxrwxrwx. 1 root root 30 Jan 31 01:58 inotify-tools -> /usr/local/inotify-tools-3.14/
- 10 drwxr-xr-x. 6 root root 4096 Jan 31 01:55 inotify-tools-3.14
- 11 drwxr-xr-x. 2 root root 4096 Sep 23 2011 lib
- 12 drwxr-xr-x. 2 root root 4096 Sep 23 2011 lib64
- 13 drwxr-xr-x. 2 root root 4096 Sep 23 2011 libexec
- 14 drwxr-xr-x. 2 root root 4096 Sep 23 2011 sbin
- 15 drwxr-xr-x. 5 root root 4096 Nov 25 02:40 share
- 16 drwxr-xr-x. 2 root root 4096 Sep 23 2011 src
- 17 [root@nfs-server local]# cd inotify-tools
- 18 [root@nfs-server inotify-tools]# ||
- 19 total 16

提示编译成功后会生成4个目录,分别是:

- 1 [root@nfs-server /]# cd /usr/local/inotify-tools
- 2 [root@nfs-server inotify-tools]# II
- 3 total 16
- 4 drwxr-xr-x. 2 root root 4096 Jan 31 01:55 bin ##inotify执行命令(二进制)
- 5 drwxr-xr-x. 3 root root 4096 Jan 31 01:55 include ##inotify程序所需用的头文件
- 6 drwxr-xr-x. 2 root root 4096 Jan 31 01:55 lib ##动态链接的库文件
- 7 drwxr-xr-x. 4 root root 4096 Jan 31 01:55 share ##帮助文档

工具集合介绍:

一共安装了2个工具(命令),即inotifywait和inotifywatch

inotifywait:在被监控的文件或目录上等待特定文件系统事件(open、close、delete等)发生,执行后处于阻塞状态,适合在 shell脚本中使用。

inotifywatch:收集被监视的文件系统使用度统计数据,指定文件系统事件发生的次数统计。

4) inotify命令常用参数详解

- 1 [root@nfs-server inotify-tools]# ./bin/inotifywait --help
- 2 inotifywait 3.14
- 3 Wait for a particular event on a file or set of files.
- 4 Usage: inotifywait [options] file1 [file2] [file3] [...]
- 5 Options:
- 6 -r|--recursive Watch directories recursively. ##递归查询目录
- 7-q|--quiet Print less (only print events) ##打印很少的信息,仅仅打印监控相关的信息
- 8 -m|--monitor Keep listening for events forever. Without
- 9 this option, inotifywait will exit after one
- 10 event is received. ##始终保持事件监听状态
- 11 --excludei <pattern>
- 12 Like --exclude but case insensitive. ##排除文件或目录时,不区分大小写
- 13 --timefmt <fmt> strftime-compatible format string for use with
- 14 %T in --format string. ##指定时间的输出格式

5) 测试监控事件

开启两个窗口

1.测试create

1第一步

2 [root@nfs-server inotify-tools]# /usr/local/inotify-tools/bin/inotifywait -mrq --timefmt '%d/%m/%y %H:%M' -- format '%T %w%f' -e create /data ##实行当前命令后,界面处于阻塞状态,只有在另外一个客户端测试时,才会显示监控状态

- 3 31/01/16 10:23 /data/ceshi.txt
- 4 31/01/16 10:24 /data/what
- 5 31/01/16 10:27 /data/a
- 6 31/01/16 10:27 /data/b
- 7 31/01/16 10:27 /data/c
- 8 31/01/16 10:27 /data/d
- 9 31/01/16 10:27 /data/e

```
10 31/01/16 10:27 /data/f
11
12 第二步:
13 克隆一个NFS客户端切换到/data目录下,新建ceshi.txt、what文件,观察监控的变化
14 [root@nfs-server data]# touch ceshi.txt
15 [root@nfs-server data]# mkdir /who
16 [root@nfs-server data]# touch what
17 [root@nfs-server data]#
18 [root@nfs-server data]# touch {a..f}
2、测试delete
1 [root@nfs-server inotify-tools]# /usr/local/inotify-tools/bin/inotifywait -mrq --timefmt '%d/%m/%y %H:%M' --
format '%T %w%f' -e delete /data ##监控/data目录删除时间
3 监控如下:
4
5 31/01/16 10:31 /data/reew.txt
6 31/01/16 10:31 /data/test1.txt
8 [root@nfs-server data]# rm -f reew.txt test1.txt ##删除这两个文件
9 [root@nfs-server data]#
3、同时测试create、delete
1 第一步:
2 [root@nfs-server inotify-tools]# /usr/local/inotify-tools/bin/inotifywait -mrq --timefmt '%d/%m/%y %H:%M' --
format '%T %w%f' -e delete,create /data
3 监控输出信息:
4 31/01/16 10:35 /data/hero.sh
5 31/01/16 10:35 /data/a
6 31/01/16 10:35 /data/f
7 31/01/16 10:36 /data/b
8 31/01/16 10:36 /data/c
9 31/01/16 10:36 /data/d
10 31/01/16 10:36 /data/e
11 第二步:
12 [root@nfs-server data]# touch hero.sh
13 [root@nfs-server data]# II
14 [root@nfs-server data]# rm -f [a..f]
15 [root@nfs-server data]# rm -f {a..f}
16 [root@nfs-server data]#
一般工作中使用到: [root@nfs-server inotify-tools]# /usr/local/inotify-tools/bin/inotifywait -mrq --timefmt
'%d/%m/%y %H:%M' --format '%T %w%f' -e delete,create,close write /data
工作环境中通过脚本实时同步:
1 #!/bin/bash
2 inotify=/usr/local/inotify-tools/bin/inotifywait
3 $inotify -mrq --timefmt '%d/%m/%y %H:%M' --format '%T %w%f' -e delete,create,close write /data
4\
5 |while read file
6 do
8 rsync -az /data --delete rsync backup@192.168.1.17::backup \
9 -- password-file = /etc/rsync.password
10 done
测试:
1 脚本属于开启状态:
2 [root@nfs-server scripts]# sh -x inotify.sh
3 + inotify=/usr/local/inotify-tools/bin/inotifywait
4 + read file
5 + /usr/local/inotify-tools/bin/inotifywait -mrq --timefmt '%d/%m/%y %H:%M' --format '%T %w%f' -e
delete, create, close write / data
```

```
6 + cd /
7 + rsync -az /data --delete rsync backup@192.168.1.17::backup --password-file=/etc/rsync.password
8 + read file
9 + cd /
10 + rsync -az /data --delete rsync backup@192.168.1.17::backup --password
11 接着在NFS客户端/data目录下创建文件
12 [root@nfs-server data]# touch {a..z}
13 [root@nfs-server data]# echo i am best >a ##修改a中的内容, 查看热备服务器是否同步
14
15 rsync热备服务器端显示如下:
16 [root@backup //]# cd /backup/
17 [root@backup backup]# cd data/
18 [root@backup data]# II
19 total 0
20 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 a
21 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 b
22 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 c
23 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 d
24 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 e
25 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 f
26 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 g
27 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 h
28 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 i
29 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 j
30 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 k
31 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 l
32 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 m
33 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 n
34 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 o
35 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 p
36 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 q
37 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 r
38 -rw-r--r-. 1 rsync rsync 0 Mar 4 2016 s
39 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 t
40 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 u
41 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 v
42 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 w
43 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 x
44 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 y
45 -rw-r--r--. 1 rsync rsync 0 Mar 4 2016 z
46 [root@backup data]# cat a
47 i am best ##显示已经实时同步过来
```

6) 优化

48 [root@backup data]#

1 [root@nfs-server scripts]# echo "50000000" >/proc/sys/fs/inotify/max_user_watches 2 [root@nfs-server scripts]# echo "50000000" >/proc/sys/fs/inotify/max queued events

结论: 经过测试, 每秒200个文件并发, 数据同步几乎无延迟(小于1秒)