# **Operator Overloading**

The material in this handout is collected from the following reference:

- Chapter 14 of the text book <u>C++ Primer</u>.
- Various sections of Effective C++.
- Various sections of More Effective C++.

#### The StopWatch class

Class Stopwatch is a simple class that keeps track of how many seconds have elapsed and is used to demonstrate operator overloading. Consider the definition of the class:

```
1 // in interface file stopwatch.h
 2 class StopWatch {
 3 public:
      StopWatch(); // default constructor
 4
 5
      StopWatch(int seconds); // conversion constructor
      StopWatch(int hours, int minutes, int seconds); // non-default ctor
 6
 7
 8
      // tell other programmers and compiler that you want default semantics
 9
      StopWatch(StopWatch const&) = default;
10
      StopWatch& operator=(StopWatch const&) = default;
      ~StopWatch() = default;
11
12
13
      void Increment(int seconds = 1);
14
     void Reset();
15
     int GetSeconds() const;
16
     void Display() const;
17
18
    private:
19
     int seconds;
20
    };
```

The member functions of class Stopwatch are defined <u>here</u>.

Suppose we have two Stopwatch objects, and we want to make a third Stopwatch object that represents the sum of the first two Stopwatch es:

```
1  StopWatch sw1(30); // 30 seconds
2  StopWatch sw2(10); // 10 seconds
3  
4  // sw3 should be 40 seconds but following line will not compile
5  StopWatch sw3 = sw1 + sw2;
```

g++ will produce this error message:

```
1 error: no match for 'operator+' in 'sw1 + sw2'
```

The code above will not compile because the compiler has no idea how to "add" two Stopwatch objects. The message doesn't necessarily say it's illegal to add to Stopwatch objects. It says that it can't find a function [operator+] that matches. The "C-style" way is to simply create a function to do the work:

```
StopWatch AddStopWatch(StopWatch const& sw1, StopWatch const& sw2) {
    // Construct unnamed StopWatch from parameters and
    // return result by value (a copy)
    return StopWatch(sw1.GetSeconds() + sw2.GetSeconds());
}
```

Here's how clients could use function AddStopWatch:

```
StopWatch sw1(30); // 30 seconds
StopWatch sw2(10); // 10 seconds
StopWatch sw3 = AddStopWatch(sw1, sw2);
sw3.Display(); // prints 00:00:40
```

This isn't all that bad for adding two objects, but it doesn't scale well:

```
1 StopWatch sw1(30); // 30 seconds
    StopWatch sw2(10); // 10 seconds
 3 StopWatch sw3(60); // 60 seconds
 4 StopWatch sw4(20); // 20 seconds
 5
 6 // We have to do this (and it will get worse with more)
 7 StopWatch tempsw1 = AddStopWatch(sw1, sw2);
    StopWatch tempsw2 = AddStopWatch(tempsw1, sw3);
9
    StopWatch sw5 = AddStopWatch(tempsw2, sw4);
10 | sw5.Display(); // 00:02:00
11
12 // we could've "chained" the calls to save some typing:
13
    StopWatch sw6 =
14
    AddStopWatch(AddStopWatch(AddStopWatch(sw1, sw2), sw3), sw4);
15 sw6.Display(); // 00:02:00
```

What we really just want to be able to do is this:

```
1 | StopWatch sw5 = sw1 + sw2 + sw3 + sw4;
```

The solution is to *instruct* or *teach* the compiler how to add Stopwatch es by overloading operator + for Stopwatch objects.

# Overloading binary + operator

To overload operator + [or most any operator for that matter], we use an *operator function*, which has the form:

```
1 | return-type operator op(argument-list)
```

where:

• return-type is the type of the function's returned value, just as with other functions.

- operator is a reserved word
- op is the operator to overload (such as +, \*, -, and so on).
- argument-list is the list of arguments to the operator function.

We simply need to create a non-member function called operator+ that takes two Stopwatch objects as parameters:

```
StopWatch operator+(StopWatch const& lhs, StopWatch const& rhs) {
    // lhs is left-hand side
    // rhs is right-hand side
    StopWatch sw(lhs.GetSeconds() + rhs.GetSeconds());

// Return the result by value (a copy)
return sw;
}
```

This makes life much simpler for clients of class Stopwatch.

- Notice that the code does exactly same thing as function AddStopwatch that was defined earlier. Only the function name has changed, really.
- Now, when the compiler sees operator + between two Stopwatch objects, it knows what to
- It calls the function and passes the two Stopwatch es as operands: left operand first, right operand second).
- Notice that the function is just a "normal" global function.
- Where should the function go? Which source file?

#### Example usage:

```
1 StopWatch sw1(30); // 30 seconds
    StopWatch sw2(10); // 10 seconds
    StopWatch sw3(60); // 60 seconds
 4 StopWatch sw4(20); // 20 seconds
 5
 6 StopWatch sw5 = sw1 + sw2;
7
    StopWatch sw6 = sw1 + sw2 + sw3 + sw4;
 8
9
   sw5.Display(); // 00:00:40
    sw6.Display(); // 00:02:00
10
11
12
    // Functional notation (this is really what's happening at runtime)
13
    StopWatch sw7 = operator+(sw1, sw2);
14 | sw7.Display(); // 00:00:40
```

In practice, the functional notation is seldom used. Essentially, overloading an operator means writing a function that the compiler will call when it sees the operator being used when at least one argument is a user-defined data type.

Again, notice how similar the functional notation is to our original function:

```
1  StopWatch sw7 = operator+(sw1, sw2);
2  StopWatch sw8 = AddStopWatch(sw1, sw2);
```

# Overloading more operators for StopWatch class

While we're at it, we'll overload some more operators. First, let's overload operator - to determine the "difference" between two Stopwatch objects:

```
1  StopWatch operator-(StopWatch const& lhs, StopWatch const& rhs) {
2   int secs = lhs.GetSeconds() - rhs.GetSeconds(); // don't want -ve
3   secs = (secs < 0) ? 0 : secs;
4   return StopWatch(secs); // Create a new one and return it
5 }</pre>
```

Test it:

```
1   StopWatch sw1(1, 30, 0); // 01:30:00
2   StopWatch sw2(10, 0, 0); // 10:00:00
3   StopWatch sw3 = sw2 - sw1; // Subtract smaller from larger
4   sw3.Display(); // 00:08:30
5   sw3 = sw1 - sw2; // Subtract larger from smaller
6   sw3.Display(); // 00:00:00
```

Simple. In a nutshell, that's about it. [Like everything in C++, there are lots of little details involved.]

How about something like this:

```
1 | StopWatch sw2 = sw1 * 2; // double the time
```

Of course, we'll get this:

```
1 | error: no match for 'operator*' in 'sw1 * 2'
```

Fair enough. Another trivial function to implement:

```
// Multiply: StopWatch * int
StopWatch operator*(StopWatch const& lhs, int rhs) {
   return StopWatch(lhs.GetSeconds() * rhs);
}
```

And the problem is solved. Or is it?

```
1 | StopWatch sw3 = 2 * sw1; // Double the time?
```

Error message:

```
error: no match for 'operator*' in '2 * sw1'
note: candidates are: StopWatch operator*(const StopWatch&, int)
```

So, we add an overload to operator\*:

```
// Multiply: int * StopWatch
StopWatch operator*(int lhs, StopWatch const& rhs) {
   return StopWatch(lhs * rhs.GetSeconds());
}
```

Let us make one more observation about the two operator\* overloads. Except for their return values, they do the same thing: they multiply a Stopwatch and an int value. That is, they're supposed to do the same thing. How can you be sure the behavior of sw\*2 is consistent with that of 2\*sw? What guarantee do you have that their implementations won't diverge over time, possibly as a result of different programmers maintaining and enhancing them? At this moment, you've no such guarantee. A design principle to guarantee both functions will give the same result is for 2\*sw to be implemented in terms of sw\*2. You or any other programmer need only maintain the sw\*2 version, because the 2\*sw version will then automatically behave in a consistent fashion:

```
Stopwatch operator*(int lhs, Stopwatch const& rhs) {
return rhs * lhs; // implement 2*sw in terms of sw*2
}
```

#### Conversion constructor and explicit keyword

How about adding an integer to a Stopwatch?

```
1 | StopWatch sw1(60); // 00:01:00
2 | StopWatch sw2 = sw1 + 60; // Add another minute?
```

Let's think about how the language has implemented the binary operator + for built-in types. The rule is very simple: both operands must have the same type. Otherwise, one of the operands is promoted or otherwise converted to the second operand's type. For example, we know that 3 + 4 will evaluate to an int value 7; that 3.1 + 4.1 will evaluate to double value 7.2; that 2.4f + 5.1f evaluates to float value 7.5f. What does the compiler do for expression 4.1 + 3? The rule is that operand 3 of type int is promoted to type double with value 3.0. That is, the compiler will evaluate the expression as 4.1 + (double)3 which is 4.1 + 3.0 with the evaluation resulting in value 7.1 of type double.

Using the knowledge of how operator + is implemented for built-in types, let's think about how the compiler evaluates expression sw1 + 60. The compiler will try to convert sw1 to an int value but it sees no function that can convert a Stopwatch object into an int object. Next, the compiler will try to convert an int object to a Stopwatch object. It finds no function in the global scope that perform the conversion. However, in the definition of Stopwatch class, it finds this function declared:

```
1 class Stopwatch {
2 public:
3 Stopwatch(int seconds);
4 // other stuff ...
5 };
```

Constructor Stopwatch(int); is a special constructor that can convert an int value into a Stopwatch. Such constructors are called *conversion constructors* and are implicitly called by the compiler when it needs to evaluate an expression consisting of Stopwatch and int values.

If you or your clients find such implicit conversions off-putting, then you can tell the compiler to only perform such conversions when *explicitly* asked to by adding the keyword <code>explicit</code> in the declaration of <code>stopwatch</code> 's constructor:

```
class StopWatch {
1
  public:
2
   // this prevents the conversion ctor from being used to perform
3
4
    // implicit type conversions, though they may still be used for
5
   // explicit conversions
     // note: use explicit keyword only for declarations
6
7
    explicit StopWatch(int seconds);
8
  // other stuff ...
9
  };
```

In this case, the compiler will flag expression [sw1 + 60] as an error. The programmer can explicitly request for the conversion like this:

Constructors declared explicit are usually preferable to non-explicit ones, because they prevent compilers from performing unexpected [and often unintended] type conversions.

Unless you've have a good reason for allowing a constructor to be used for implicit type conversions, declare it explicit.

#### Test your knowledge

Given the following overloads for class StopWatch:

```
// Multiply: StopWatch * int
1
   StopWatch operator*(StopWatch const& lhs, int rhs) {
2
3
     return StopWatch(lhs.GetSeconds() * rhs);
4
   }
5
  // Multiply: int * StopWatch
6
7
   StopWatch operator*(int lhs, StopWatch const& rhs) {
8
     return rhs * lhs; // Simply reverse the operands
9
  }
```

explain whether the compiler will flag the following code as error?

```
1 StopWatch sw1(60);
2 StopWatch sw2(10);
3 StopWatch sw3 = sw1 * sw2; // Multiply two StopWatches
```

#### Pointers vs references

By now it should be very obvious why we are passing references instead of pointers with these overloaded operator functions. If we used pointers, we'd have to use the address-of operator every time we used them. For example, we'd have to do this:

```
1 | StopWatch sw3 = &sw1 * &sw2;
```

which would be very undesirable [not to mention, illegal, as you can't multiply pointers].

### Overloaded operators as member functions

Up to this point, all of our overloading was done with functions that are not member functions of class Stopwatch. We could do this because class Stopwatch has declared a public member function GetSeconds:

```
1 StopWatch operator+(StopWatch const& lhs, StopWatch const& rhs) {
2   return StopWatch(lhs.GetSeconds() + rhs.GetSeconds());
3 }
```

If this method wasn't available, none of this would work. One solution would be to declare additional member functions in class Stopwatch:

```
1 | class StopWatch {
 2
    public:
    // other function from before ...
 3
 4
     // Overloaded operators (member functions). Notice the const at the end.
 6
      StopWatch operator+(StopWatch const& rhs) const;
 7
      StopWatch operator-(StopWatch const& rhs) const;
8
      StopWatch operator*(int rhs) const;
9
10
   private:
11
     int seconds;
    };
```

The functions will be defined in implementation file stopwatch.cpp:

```
StopWatch StopWatch::operator+(StopWatch const& rhs) const {
1
2
      return StopWatch(seconds + rhs.seconds);
    }
3
4
5
    StopWatch StopWatch::operator-(StopWatch const& rhs) const {
      return StopWatch(seconds - rhs.seconds);
6
7
    }
8
9
   StopWatch StopWatch::operator*(int rhs) const {
10
      return StopWatch(seconds * rhs);
11
   }
```

Notice that the methods are accessing the private data from the **stopwatch** object that was passed in to them. This is allowed because the function is a member of class **Stopwatch**.

All of this code works as before:

```
1
    void f1() {
 2
      StopWatch sw1(30);
 3
      StopWatch sw2(10);
 4
      StopWatch sw3 = sw1 + sw2; // StopWatch sw3 = sw1.operator+(sw2);
 5
      StopWatch sw4 = sw1 + 20; // StopWatch sw4 = sw1.operator+(20);
      StopWatch sw5 = sw1 - sw2; // StopWatch sw5 = sw1.operator-(sw2);
 6
 7
      StopWatch sw6 = sw1 - 20; // StopWatch sw6 = sw1.operator-(20);
 8
      StopWatch sw7 = sw1 * 10; // StopWatch sw7 = sw1.operator*(10);
 9
10
      sw3.Display(); // 00:00:40;
     sw4.Display(); // 00:00:50;
11
      sw5.Display(); // 00:00:20;
12
13
      sw6.Display(); // 00:00:10;
      sw7.Display(); // 00:05:00;
14
15
    }
```

Notice which object the method is invoked on. This:

```
1 | StopWatch sw3 = sw1 + sw2;
```

is the same as:

```
1  // Method is invoked on left object
2  StopWatch sw3 = sw1.operator+(sw2);
```

and not this:

```
1  // This is NOT how it works.
2  StopWatch sw3 = sw2.operator+(sw1);
```

It is **not** random, it is **not** arbitrary, it is **not** which ever object the compiler chooses. It is **always** the left object [with a binary operator]. *Always*.

What about this now?

```
1 StopWatch sw1(30);
2
3  // What about this?
4 StopWatch sw2 = 2 + sw1;
```

With the global function, the functional notation looks like this:

```
1 | StopWatch sw2 = operator+(2, sw1);
```

which converts to this [using the conversion constructor]:

```
1 | StopWatch sw2 = operator+(StopWatch(2), sw1);
```

But with built-in types, there are no member functions, so it can't even attempt this:

```
1 | StopWatch sw2 = 2.operator+(sw1);
```

This sometimes makes global functions more useful than member functions.

# Overloading operator <<

Although Stopwatch::Display member function is nice, we'd like to write characters to the standard output stream the C++ way:

Defining output operator << for a given type is typically trivial. Here is a simple output operator for Stopwatch that simply prints data similar to Stopwatch::Display:

```
1 std::ostream& operator<<(std::ostream& os, StopWatch const& sw) {
     int total_seconds = sw.GetSeconds(); // get seconds
 3
     int hours = total_seconds / 3600; // hrs
4
     int minutes = (total_seconds - (hours * 3600)) / 60; // mins
     int seconds = total_seconds % 60; // secs
 5
 6
 7
     os.fill('0'); // print them
8
     os << std::setw(2) << hours << ':';
9
    os << std::setw(2) << minutes << ':';
     os << std::setw(2) << seconds << "\n";
10
11
      return os; // must return the ostream reference
12
13
    }
```

Given the above definition of operator << for class Stopwatch, the meaning of

```
1 | std::cout << sw1; // infix notation
```

where sw1 is a Stopwatch object is just the call

```
1 | operator<<(std::cout, sw1); // functional notation</pre>
```

Note how operator<<() takes an ostream& as its first argument and returns it again as its return value. That's the way the output stream is passed along so that you can "chain" output operations. For example, we could output two stopwatch es like this:

```
StopWatch sw1(60);
StopWatch sw2(100);
std::cout << sw1 << sw2;</pre>
```

This will be handled by first resolving the first << and after that the second << [because left-shift operator << is left associative]

That is, first output sw1 to std::cout and then output sw2 to the output stream that is the result of the first output operation. In fact, we can use any of those three variants to write out sw1 and sw2. We know which one is easier to read, though.

What if member function <code>StopWatch::GetSeconds</code> was removed [or made private]? Should method <code>operator<<</code> be made a member function of class <code>StopWatch</code>? This is what the functional notation looks like for a member function:

```
1 | std::cout.operator<<(sw1); // Functional notation (member function)
```

See the problem? We can't make it a member function of class Stopwatch. It would need to be a member of class ostream, which we cannot modify. Therefore, overload function operator<< will have to be implemented as a non-member function of class Stopwatch.

# The friend keyword

Since we can't make output operator operator << a member of class ostream, we need a way to allow the overloaded output operator function to access private members of class Stopwatch. We do this by making the overloaded output operator a *friend* of class Stopwatch. A function that is not a member of a class can be granted access to all members through a friend declaration. For example:

```
1 class StopWatch {
2 public:
    // other public stuff ...
3
5
    // make this function a friend so it can access private members of this
   class
6
    friend std::ostream& operator<<(std::ostream& os, const StopWatch& rhs);</pre>
7
8
    private:
9
    int seconds;
10
   };
```

The definition of operator<< would look like this:

```
std::ostream& operator<<(std::ostream& os, StopWatch const& sw){</pre>
2
     // A friend can access private members of sw
 3
      int hours = sw.seconds / 3600;
 4
     int minutes = (sw.seconds - (hours * 3600)) / 60;
 5
     int seconds = sw.seconds % 60;
 6
7
     os.fill('0'); // Print them
     os << std::setw(2) << hours << ':';
8
9
     os << std::setw(2) << minutes << ':';
      os << std::setw(2) << seconds << "\n";
10
11
      return os; // Must return a reference to the ostream
12
13
   }
```

Just like in the Real World, friendship is a one-way street: "I may be your friend, but that doesn't make you my friend." Friendship is granted from one entity to another. With operator<<, class Stopwatch is granting friendship to the operator [the operator is NOT granting friendship to class Stopwatch]. If you need it to work both ways, then both entities must grant the friendship.

Friendship is an advanced technique and should be limited to operator<< until you have a very good understanding of C++ class design. In other words, it should be used as a last resort

# Automatic conversions and user-defined types

Recall that a single-argument constructor is called a *conversion constructor* because it "converts" its argument into an object of the class type.

```
void f1() {
    StopWatch sw1; // Default constructor
    sw1 = 60; // same as sw1 = (StopWatch)60;
    // same as sw1 = StopWatch(60);
}
```

Another example:

```
void fooSW(const StopWatch& sw) {
sw.Display(); // Do something with sw
}

StopWatch sw1(60);
fooSW(sw1); // Pass StopWatch
int time = 90;
fooSW(time); // Convert int to StopWatch
```

Both examples *implicitly* convert the integer to a Stopwatch; implicitly meaning automatically and silently. However, the opposite isn't the same thing:

What to do? Same as always, create **Y**et **A**nother **F**unction. We'll call the function **ToInt** because it will convert a **Stopwatch** into an **int**:

```
class StopWatch {
public:
    // other public methods from before ...
int ToInt() const; // convert to int (explicit)

private:
    int seconds;
};
```

The function is defined outside the class definition like this [notice that the function definition must specify the const keyword]:

```
1 int StopWatch::ToInt() const {
2   return seconds;
3 }
```

You use member function Stopwatch::ToInt like this:

```
void f2() {
    Stopwatch sw1(60);
    int seconds = sw1.ToInt(); // convert to an int explicitly
    std::cout << seconds << "\n";
}</pre>
```

If you want the compiler to perform the conversions *automatically*, then you have to use an *implicit type conversion operator*. An implicit type conversion operator is simply a member function with a strange-looking name: the word operator followed by a type specification. You aren't allowed to specify a type for the function's return value, because the type of the return value is basically just the name of the function. For example, to allow Stopwatch objects to be implicitly converted to ints, you might define class Stopwatch like this:

```
class StopWatch {
public:
    // other public methods ...
    operator int() const; // implicit type conversion operator

private:
    int seconds;
};
```

The type conversion operator is trivially defined:

```
1 | StopWatch::operator int() const {
2    return seconds;
3 | }
```

This function would be automatically invoked in contexts like this:

```
void f3() {
    StopWatch sw1(60);
    int seconds = sw1; // Convert to an int implicitly
    std::cout << seconds << std::endl;
}</pre>
```

Let's review the general form of the type conversion operator:

```
1 | operator type() const;
```

• type can be a built-in type such as int or a user-defined type such as std::string or Stopwatch.

- *Must* be a member function. Most other operators can be overloaded as either a member function or global function.
- Zero arguments. You may specify void for the arguments, but it's not required.
- *No* return type because the type of the return value is basically just the function's name.
- Can be marked explicit to prevent the compiler from making the conversion implicitly:

```
1 | explicit operator int() const;
```

• Conversion operators are generally marked const.

# Be wary of type conversion operator

In general, you usually don't want to provide type conversion functions of *any* ilk. The fundamental problem is that such functions often end up being called when you neither want nor expect them to be. The result can be incorrect and unintuitive program behavior that is maddeningly difficult to diagnose. Here's an example:

```
int array[10];
stopWatch sw(60);
// other code...
int value = array[sw]; // disaster: sw converted to 60!!!
std::cout << value << "\n";
int swval = sw
std::cout << swval << "\n";</pre>
```

Further suppose you forgot to write an operator << for class Stopwatch. You would probably expect that the attempt to print sw would fail, because there is no appropriate operator << to call:

```
1 | StopWatch sw(60);
2 | std::cout << sw;</pre>
```

You would be mistaken. Your compilers, faced with a call to a function called <code>operator<<</code> that takes a <code>StopWatch</code>, would find that no such function existed, but they would then try to find an acceptable sequence of implicit type conversions they could apply to make the call succeed. The rules defining which sequences of conversions are acceptable are complicated, but in this case your compilers would discover they could make the call succeed by implicitly converting <code>sw</code> to an <code>int</code> by calling <code>StopWatch::operator int()</code>. The result of the code above would be to print <code>sw</code> as an <code>int</code>, not as a stopwatch. This is hardly a disaster, but it demonstrates the disadvantage of implicit type conversion operators: their presence can lead to the <code>wrong function</code> being called [that is, one other than the one intended].

The solution is to replace the operators with equivalent functions that don't have the syntactically magic names. For example, to allow conversion of a Stopwatch object to an int, replace operator int with the previously defined member function Stopwatch::ToInt:

```
int array[10];
stopWatch sw(60);

// other code...
int temp2 = 0;
int value = array[temp2]; // correct
std::cout << value << "\n";
int swval = sw.ToInt(); // explicit
std::cout << swval << "\n";</pre>
```

The other alternative is to instruct the compiler not to implicitly convert a Stopwatch to an int by specifying the implicit type conversion operator to be explicit:

```
class Stopwatch {
public:
    Stopwatch();
    explicit Stopwatch(int seconds); // suppress implicit conversions
    Stopwatch(int hrs, int mins, int secs);
    // other public methods

private:
    int seconds;
};
```

In this case, the compiler must be instructed to perform the conversion from a Stopwatch object to an int value:

In most cases, the inconvenience of having to call conversion functions explicitly is more than compensated for by the fact that unintended functions can no longer be silently invoked. In general, the more experience C++ programmers have, the more likely they are to eschew type conversion operators. The members of the committee working on the C++ standard library, for example, are among the most experienced in the business, and perhaps that's why the string type they added to the library contains no implicit conversion from a string object to a C-style char\*. Instead, there's an explicit member function, c\_str, that performs that conversion. Coincidence? I think not.

### **Overloading operators with side-effects**

Up to this point:

- All of our operators created a new object.
- This new object was returned by value.
- The operands were not modified in anyway [which makes sense].

Consider the following two examples:

```
// built-in types that implicitly support operator+
int a = 1, b = 2, c;
c = a + b; // new value stored in c; a and b are unchanged

// StopWatch type overloads operator+
StopWatch sw1(30), sw2(60);
StopWatch sw3 = sw1 + sw2; // new StopWatch object is created
// sw1 and sw2 unchanged
```

We would like to support *side-effect* operators like this:

```
// built-in operators that are implicitly support operator+=
int a = 5, b = 7;
a += b; // a is changed; b is unchanged

// StopWatch type must overload operator+=
StopWatch sw1(30), sw2(60);
sw1 += sw2; // sw1 is changed; sw2 is unchanged
```

Member functions operator+ and operator+= are declared like this:

```
1 class StopWatch {
public:
3
     // overloads for op+ and op+=
     Stopwatch operator+(Stopwatch const& rhs) const;
5
     StopWatch& operator+=(StopWatch const& rhs);
6
7
     // other public methods ...
8
9 private:
10
    int seconds;
11
   };
```

These overloads are defined like this:

```
Stopwatch Stopwatch::operator+(Stopwatch const& rhs) const {
   return Stopwatch(seconds + rhs.seconds);
}

Stopwatch& Stopwatch::operator+=(Stopwatch const& rhs) {
   seconds += rhs.seconds; // Modify this object directly
   return *this;
}
```

Member function operator+= is not marked const because you're changing the object. The return type is a reference because a new object is not being created. In addition, returning a reference must support this syntax that is valid with ints and must therefore be valid with Stopwatch es:

```
1  int a = 1, b = 2, c = 3;
2  a += b += c; // associates right to left; changes a and b
3  std::cout << a << "\n"; // 6
4  std::cout << b << "\n"; // 5
5  std::cout << c << "\n"; // 3
6
7  StopWatch sw1(30), sw2(60), sw3(90);
8  sw1 += sw2 += sw3; // associates right to left; changes sw1 and sw2
9  std::cout << "\n"; // 00:03:00
10  std::cout << "\n"; // 00:02:30
11  std::cout << "\n"; // 00:01:30</pre>
```

If the function returned void, this syntax would be illegal. Since this is a *pointer* to the object, \*this is the object, and that's what you want to return a reference to. You'll see this technique used more later.

# Not a good idea to overload &&, |||, and , operators

C++ allows you to customize the behavior of operators && and []] for user-defined types. You do it by overloading functions operator& and operator[], and you can do this at the global scope or on a per-class basis. If you decide to take advantage of this opportunity, however, you must be aware that you are changing the rules of the game quite radically, because you are replacing short-circuit semantics with *function call* semantics. That is, if you overload operator&, what looks to you like this:

```
1 | if (expression1 && expression2) ...
```

looks to compilers like one of these:

```
// when operator&& is a member function
(expression1.operator&&(expression2)) ...

// when operator&& is a global function
(operator&&(expression1, expression2)) ...
```

This may not seem like that big a deal, but function call semantics differ from short-circuit semantics in two crucial ways. First, when a function call is made, *all* parameters must be evaluated, so when calling functions operator& and operator | | , both parameters are evaluated. There is, in other words, no short circuit evaluation. Second, the language specification leaves undefined the order of evaluation of function call arguments, so there is no way of knowing whether expression1 or expression2 will be evaluated first. This stands in stark contrast to short-circuit evaluation, which *always* evaluates its arguments in left-to-right order.

As a result, if you overload && or |||, there is no way to offer programmers the behavior they both expect and have come to depend on. So don't overload && or |||.

The comma operator is used to form *expressions*, and you're most likely to run across it in the update part of a for loop. Consider the following example:

```
1  // reverse string s in place
2  void reverse(char s[]) {
3    for (int i = 0, j = strlen(s)-1; i < j; ++i, --j) {
4      int c = s[i];
5      s[i] = s[j];
6      s[j] = c;
7    }
8  }</pre>
```

Here, i is incremented and j is decremented in the final part of the for loop. It is convenient to use the comma operator here, because only an expression is valid in the final part of a for loop; separate statements to change the values of i and j would be illegal.

Just as there are rules in C++ defining how & and | | behave for built-in types, there are rules defining how the comma operator behaves for such types. An expression containing a comma is evaluated by first evaluating the part of the expression to the left of the comma, then evaluating the expression to the right of the comma; the result of the overall comma expression is the value of the expression on the right. So in the final part of the loop above, compilers first evaluate ++i, then --j, and the result of the comma expression is the value returned from --j.

If you decide to write your own comma operator, you will need to mimic this behavior. Unfortunately, you can't perform the requisite mimicry. If you write operator, as a non-member function, you'll never be able to guarantee that the left-hand expression is evaluated before the right-hand expression, because both expressions will be passed as arguments in a function call (to operator,). But you have no control over the order in which a function's arguments are evaluated. So the non-member approach is definitely out. That leaves only the possibility of writing operator, as a member function. Even here you can't rely on the left-hand operand to the comma operator being evaluated first, because compilers are not constrained to do things that way. Hence, you can't overload the comma operator and also guarantee it will behave the way it's supposed to. It therefore seems imprudent to overload it at all.

Don't overload operators , , &&, and | !!!

# Overloading prefix and postfix increment and decrement operators

Both prefix and postfix versions of the increment operator use the same token ++ and must be overloaded. Likewise the prefix and postfix versions of the decrement operator use the same token --. Overloaded functions are differentiated on the basis of the parameter types they take, but neither prefix nor postfix increment or decrement takes an argument. To surmount this linguistic conundrum, it was decreed that postfix forms take an int argument, and compilers silently pass 0 as that int when those functions are called:

```
class StopWatch {
2
    public:
3
     // other functions ...
     StopWatch& operator++(); // prefix ++
4
5
     const StopWatch operator++(int); // postfix ++
6
7
     StopWatch& operator--();
                                      // prefix --
8
     const StopWatch operator--(int); // postfix --
9
10
   private:
11
    int seconds;
```

You may recall that the prefix form of the increment operator is sometimes called *increment and fetch*, while the postfix form is often known as *fetch and increment*. These two phrases are important to remember, because they all but act as formal specifications for how prefix and postfix increment should be implemented:

```
1 // prefix form: increment and fetch
2
  StopWatch& StopWatch::operator++() {
3
     ++seconds;
                                           // increment
                                            // fetch
4
    return *this;
5 }
6 // postfix form: fetch and increment
7 const StopWatch StopWatch::operator++(int) {
     StopWatch oldValue = *this;
                                             // fetch
9
    ++(*this);
                                            // increment
10
     return oldValue;
                                             // return what was
11
   }
                                             // fetched
```

Note how the postfix operator makes no use of its parameter. This is typical. The only purpose of the parameter is to distinguish prefix from postfix function invocation. Many compilers issue warnings if you fail to use named parameters in the body of the function to which they apply, and this can be annoying. To avoid such warnings, a common strategy is to omit names for parameters you don't plan to use; that's what's been done above.

It's clear why postfix increment must return an object [it's returning an old value], but why a const object? Imagine that it did not. Then the following would be legal:

This is the same as

```
1 | sw.operator++(0).operator++(0);
```

and it should be clear that the second invocation of operator++ is being applied to the object returned from the first invocation.

There are two problems with this. First, it's inconsistent with the behavior of the built-in types. A good rule to follow when designing classes is *when in doubt, do as the* ints do, and the ints most certainly do not allow double application of postfix increment:

```
1 | int i;
2 | i++++; // error!
```

The second reason is that double application of postfix increment almost never does what clients expect it to. As noted above, the second application of operator++ in a double increment changes the value of the object returned from the first invocation, *not* the value of the original object. Hence, if

```
1 | i++++;
```

were legal, i would be incremented only once. This is counterintuitive and confusing [for both ints and Stopwatchs], so it's best prohibited.

C++ prohibits it for ints, but you must prohibit it yourself for classes you write. The easiest way to do this is to make the return type of postfix increment a const object. Then when compilers see

```
1 | i++++; // same as i.operator++(0).operator++(0);
```

they recognize that the <code>const</code> object returned from the first call to <code>operator++</code> is being used to call <code>operator++</code> again. <code>operator++</code>, however, is a non-const member function, so <code>const</code> objects - such as those returned from postfix <code>operator++</code> - can't call it. If you've ever wondered if it makes sense to have functions return <code>const</code> objects, now you know: sometimes it does, and postfix increment and decrement are examples.

Let's evaluate the postfix increment function from the perspective of efficiency. That function has to create a temporary object for its return value, and the implementation above also creates an explicit temporary object (oldvalue) that has to be constructed and destructed. The prefix increment function has no such temporaries. This leads to the conclusion that, for efficiency reasons alone, clients of Stopwatch should prefer prefix increment to postfix increment unless they really need the behavior of postfix increment. Let us be explicit about this:

When dealing with user-defined types, prefix increment should be used whenever possible, because it's inherently more efficient.

Let us make one more observation about the prefix and postfix increment operators. Except for their return values, they do the same thing: they increment a value. How can you be sure the behavior of postfix increment is consistent with that of prefix increment? What guarantee do you have that their implementations won't diverge over time, possibly as a result of different programmers maintaining and enhancing them? Unless you've followed the design principle embodied by the code above, you have no such guarantee. That principle is that postfix increment and decrement should be implemented *in terms of* their prefix counterparts. You then need only maintain the prefix versions, because the postfix versions will automatically behave in a consistent fashion.

Here is some code that makes calls to the overloaded prefix and postfix increment functions:

```
StopWatch sw1(60);
 2
    StopWatch sw2 = ++sw1; // prefix increment: afterwards sw2 == sw1
 3
    std::cout << sw1; // 00:01:01
    std::cout << sw2; // 00:01:01
 6 | sw2 = sw1++; // postfix increment: afterwards sw2 != sw1
 7
    std::cout << sw1; // 00:01:02
    std::cout << sw2; // 00:01:01
8
9
10 | sw2 = ++sw1++; // error: same as this: ++(sw1++)
11 | sw2 = (++sw1)++; // prefix followed by postfix increment
12 | std::cout << sw1; // 00:01:04
13 | std::cout << sw2; // 00:01:03
```

# Member, friend, or non-member?

In most cases, you have three choices when overloading operators: member or friend or non-member/non-friend function.

1. Member function: Binary operators will take one operand with the left operand implicit via the this pointer.

```
StopWatch StopWatch::operator*(int factor) const {
StopWatch sum(seconds_ * factor);
return sum;
}
```

Unary operators will not take any parameters.

2. Friend function: Declare a friend function to overload the operator and implement it outside of the class. The friend function has access to the private members of the parameters. Binary operators will have two operands while unary operators will have one operand.

```
StopWatch operator*(int factor, StopWatch const& sw) {
return StopWatch(sw.seconds * factor);
}
```

3. Non-member/non-friend function: Implement a non-member, non-friend function to overload the operator. The function can only access the public methods of the class which means that the class must have a public accessor. Binary operators will have two operands while unary operators will have one operand.

```
StopWatch operator*(int factor, StopWatch const& sw) {
return StopWatch(sw.GetSeconds() * factor);
}
```

4. In certain cases, a non-member, non-friend function can be implemented in terms of a regular overloaded operator function. For example, assuming a member operator\*(int) overload, the non-member/non-friend function can be defined like this:

```
1 StopWatch operator*(int factor, StopWatch const& sw) {
2   // the compiler sees it like this: sw.operator*(factor)
3   return sw * factor;
4 }
```

This assumes that the operator is commutative. That is a\*b is the same as b\*a.

Study these four functions above and be sure you understand exactly how each one is different and why. Also make sure you know why some functions have 1 parameter and some have 2 parameters. Unary operators will have 0 or 1 parameter(s), depending on whether they are members or not.

### Restrictions on operator overloading

1. At least one operand must be a user-defined type. This means you can't overload built-in types.

```
1 // compiler error: cannot overload built-in operators for int
2 int operator+(int left, int right);
```

2. You can't violate the C++ syntax rules for the operator you wish to overload. This means that you can't change the precedence or associativity of an operator. This also means that if you overload binary modulus operator [%], you can't use it with just a single operand:

```
1 int i;
2 StopWatch sw;
3
4 % i; // error: % requires 2 integer operands
5 % sw; // error: % would require 2 operands
```

- 3. You can't create new operator symbols. As mentioned above, the @ symbol is not a C++ operator for the built-in types, so you can't define it for a user-defined type.
- 4. You cannot overload the following operators: ::, .\*, ., ?:, sizeof, typeid, const\_cast, dynamic\_cast, reinterpret\_cast, and static\_cast.
- 5. The following operators can only be overloaded with member functions: =, (), [], ->.
- 6. These operators can be overloaded using either member or non-member functions:

```
1
                                      2
       1
                           +=
3
  /=
       %=
                 &=
                     = <<
            Λ=
                                >>
                                     >>=
                      >=
 <<=
       ==
           !=
                 <=
                           &&
                                \Pi
                                     ++
                      ()
                          []
                                     delete
6 new [] delete []
```

- 7. A binary operator must be implemented either by a member function taking one parameter or by a non-member function taking two parameters. The exceptions are these operators [=, (), [], ->] that must be implemented as member functions.
- 8. A unary operator must be implemented either by a member function taking no parameters or by a non-member function taking one parameter.
- 9. Remember that friend functions are non-member functions so they can't be marked const.
- 10. Operators &&, | | |, and | |, have special properties with built-in types. Namely, they are sequence guarantee operators. However, when overloaded with user-defined types, this property does not hold.

### StopWatch class implementation

```
#include <iostream>
2 #include <iomanip>
   #include "StopWatch.h"
 5 StopWatch::StopWatch() : seconds(0) {}
 6 StopWatch::StopWatch(int secs) : seconds(secs) {}
7 StopWatch::StopWatch(int hour, int minutes, int secs)
    : seconds(hour*3600 + minutes*60 + secs) {}
   void StopWatch::Increment(int secs) {
9
      seconds += secs;
10
11
12
   void StopWatch::Reset() {
13
      seconds = 0;
14 }
15
   void StopWatch::Display() const {
16
     int hours = seconds / 3600;
17
     int minutes = (seconds - (hours * 3600)) / 60;
18
     int secs = seconds % 60;
19
20
     std::cout.fill('0');
21
    std::cout << std::setw(2) << hours << ':';</pre>
22
     std::cout << std::setw(2) << minutes << ':';</pre>
23
      std::cout << std::setw(2) << secs << "\n";</pre>
24 }
25
26 int StopWatch::GetSeconds() const {
27
     return seconds;
28 }
```