

Transport Layer


Slides are adapted from the companion website of the book *Computer Networking: A Top-Down Approach* by Jim Kurose, Keith Ross

Transport layer: overview

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

Transport services and protocols



- provide *logical communication* between application processes running on different hosts
- transport protocols actions in end systems:
 - sender: breaks application messages into *segments*, passes to network layer
 - receiver: reassembles segments into messages, passes to application layer
- two transport protocols available to Internet applications
 - TCP, UDP



Transport Layer Actions

Sender:



- is passed an application-layer message
- determines segment header fields values
- creates segment
- passes segment to IP



Transport Layer Actions


Receiver:

- receives segment from IP
- checks header values
- extracts application-layer message
- demultiplexes message up to application via socket




Two principal Internet transport protocols


- **TCP:** Transmission Control Protocol
 - reliable, in-order delivery
 - congestion control
 - flow control
 - connection setup
- **UDP:** User Datagram Protocol
 - unreliable, unordered delivery
 - no-frills extension of “best-effort” IP
- services not available:
 - delay guarantees
 - bandwidth guarantees





Transport layer: overview


- Transport-layer services
- **Multiplexing and demultiplexing**
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control












Multiplexing/demultiplexing

multiplexing at sender:

handle data from multiple sockets, add transport header (later used for demultiplexing)


demultiplexing at receiver:

use header info to deliver received segments to correct socket



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries one transport-layer segment
 - each segment has source, destination port number
- host uses *IP addresses & port numbers* to direct segment to appropriate socket



Connectionless demultiplexing

Recall:

- when creating socket, must specify *host-local* port #:

```
DatagramSocket mySocket1  
= new DatagramSocket(1234);
```

- when creating datagram to send into UDP socket, must specify
 - destination IP address
 - destination port #

when receiving host receives UDP segment:

- checks destination port # in segment
- directs UDP segment to socket with that port #




IP/UDP datagrams with *same dest. port #*, but different source IP addresses and/or source port numbers will be directed to *same socket* at receiving host

Connectionless demultiplexing: an example

```
DatagramSocket mySocket2 =  
new DatagramSocket  
(9157);
```

```
DatagramSocket  
serverSocket = new  
DatagramSocket  
(6428);
```


```
DatagramSocket mySocket1 =  
new DatagramSocket (5775);
```



Connection-oriented demultiplexing

- TCP socket identified by **4-tuple**:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- demux: receiver uses *all four values (4-tuple)* to direct segment to appropriate socket
- server may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
 - each socket associated with a different connecting client

Connection-oriented demultiplexing: example



Three segments, all destined to IP address: B,
dest port: 80 are demultiplexed to *different* sockets

Summary

- Multiplexing, demultiplexing: based on segment, datagram header field values
- **UDP:** demultiplexing using destination port number (only)
- **TCP:** demultiplexing using 4-tuple: source and destination IP addresses, and port numbers
- Multiplexing/demultiplexing happen at *all* layers

Transport layer: overview

- Transport-layer services
- Multiplexing and demultiplexing
- **Connectionless transport: UDP**
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

UDP: User Datagram Protocol

- “no frills,” “bare bones” Internet transport protocol
- “best effort” service, UDP segments may be:
 - lost
 - delivered out-of-order to app
- *connectionless*:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others


Why is there a UDP?

- no connection establishment (which can add RTT delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control
 - UDP can blast away as fast as desired!
 - can function in the face of congestion


UDP: User Datagram Protocol

- UDP use:
 - streaming multimedia apps (loss tolerant, rate sensitive)
 - DNS
 - SNMP
- If reliable transfer needed over UDP:
 - add needed reliability at application layer
 - add congestion control at application layer


UDP: User Datagram Protocol [RFC 768]



UDP: Transport Layer Actions




UDP: Transport Layer Actions




UDP sender actions:

- is passed an application-layer message
- determines UDP segment header fields values
- creates UDP segment
- passes segment to IP

SNMP server




UDP: Transport Layer Actions




UDP receiver actions:

- receives segment from IP
- checks UDP checksum header value
- extracts application-layer message
- demultiplexes message up to application via socket

SNMP server




UDP segment header



UDP checksum

Goal: detect errors (*i.e.*, flipped bits) in transmitted segment

	1 st number	2 nd number	sum
Transmitted:	5	6	11



UDP checksum

Goal: detect errors (*i.e.*, flipped bits) in transmitted segment

sender:

- treat contents of UDP segment (including UDP header fields and IP addresses) as sequence of 16-bit integers
- **checksum:** addition (one's complement sum) of segment content
- checksum value put into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - Not equal - error detected
 - Equal - no error detected. *But maybe errors nonetheless?* More later

Internet checksum: an example

example: add two 16-bit integers

	1	1	1	0	0	1	1	0	0	1	1	0	0	1	1	0
	1	1	0	1	0	1	0	1	0	1	0	1	0	1	0	1
<hr/>																
wraparound	1	1	0	1	1	1	0	1	1	1	0	1	1	1	0	1
<hr/>																
sum	1	0	1	1	1	0	1	1	1	0	1	1	1	1	0	0
checksum	0	1	0	0	0	1	0	0	0	1	0	0	0	0	1	1

Note: when adding numbers, a carryout from the most significant bit needs to be added to the result

Internet checksum: not the best protection

example: add two 16-bit integers

	1	1	1	0	0	1	1	0	0	1	1	0	0	1	1	0	1	0	1
	1	1	0	1	0	1	0	1	0	1	0	1	0	1	1	0	1	0	1
<hr/>																			
wraparound	1	1	0	1	1	1	0	1	1	1	0	1	1	1	0	1	1	0	1
sum	1	0	1	1	1	0	1	1	1	0	1	1	1	1	1	0	0	0	0
checksum	0	1	0	0	0	1	0	0	0	1	0	0	0	0	0	1	1	0	0

Even though numbers have changed (bit flips), **no** change in checksum!


Summary: UDP

- “no frills” protocol:
 - segments may be lost, delivered out of order
 - best effort service: “send and hope for the best”
- UDP has its pluses:
 - no setup/handshaking needed (no RTT incurred)
 - can function when network service is compromised
 - helps with reliability (checksum)
- build additional functionality on top of UDP in application layer

Transport layer: overview


- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- **Principles of reliable data transfer**
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control

Principles of reliable data transfer




reliable service *abstraction*

Principles of reliable data transfer




Reliable data transfer protocol (rdt): interfaces


rdt_send(): called from above, (e.g., by app.). Passed data to deliver to receiver upper layer




deliver_data(): called by rdt to deliver data to upper layer



udt_send(): called by rdt to transfer packet over unreliable channel to receiver




Bi-directional communication over unreliable channel



rdt_rcv(): called when packet arrives on receiver side of channel



Reliable data transfer: getting started

- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow in both directions!
- use finite state machines (FSM) to specify sender, receiver



rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate* FSMs for sender, receiver:
 - sender sends data into underlying channel
 - receiver reads data from underlying channel




rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - checksum (e.g., Internet checksum) to detect bit errors
- *the question:* how to recover from errors?
 - *acknowledgements (ACKs):* receiver explicitly tells sender that pkt received OK
 - *negative acknowledgements (NAKs):* receiver explicitly tells sender that pkt had errors
 - sender *retransmits* pkt on receipt of NAK


stop and wait

sender sends one packet, then waits for receiver response

rdt2.0: FSM specifications




rdt2.0: FSM specification




Note: “state” of receiver (did the receiver get my message correctly?) isn’t known to sender unless somehow communicated from receiver to sender

- that’s why we need a protocol!

rdt2.0: operation with no errors



rdt2.0: corrupted packet scenario



rdt2.0 has a fatal flaw!


what happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- sender adds *sequence number* to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

rdt2.1: sender, handling garbled ACK/NAKs



rdt2.1: receiver, handling garbled ACK/NAKs



rdt2.1: discussion

sender:

- seq # added to pkt
- two seq. #s (0,1) will suffice.
Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must “remember” whether “expected” pkt should have seq # of 0 or 1

receiver:


- must check if received packet is duplicate
 - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can *not* know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must *explicitly* include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK:
retransmit current pkt

As we will see, TCP uses this approach to be NAK-free

rdt2.2: sender, receiver fragments



rdt3.0: channels with errors *and* loss

New channel assumption: underlying channel can also *lose* packets (data, ACKs)

- checksum, sequence #s, ACKs, retransmissions will be of help ...
but not quite enough


rdt3.0: channels with errors *and* loss

Approach: sender waits “reasonable” amount of time for ACK


- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but seq #s already handles this!
 - receiver must specify seq # of packet being ACKed
- use countdown timer to interrupt after “reasonable” amount of time




rdt3.0 sender




rdt3.0 sender



rdt3.0 in action




(a) no loss




(b) packet loss

rdt3.0 in action



(c) ACK loss




(d) premature timeout/ delayed ACK

Performance of rdt3.0 (stop-and-wait)

- U_{sender} : *utilization* – fraction of time sender busy sending
- example: 1 Gbps link, 15 ms prop. delay, 8000 bit packet
 - time to transmit packet into channel:


$$D_{\text{trans}} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

rdt3.0: stop-and-wait operation



rdt3.0: stop-and-wait operation

$$\begin{aligned} U_{\text{sender}} &= \frac{L / R}{2 * d_{\text{prop}} + L / R} \\ &= \frac{.008}{30.008} \\ &= 0.00027 \end{aligned}$$




- rdt 3.0 protocol performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

rdt3.0: pipelined protocols operation


pipelining: sender allows multiple, “in-flight”, yet-to-be-acknowledged packets

- range of sequence numbers must be increased
- buffering at sender and/or receiver



(a) a stop-and-wait protocol in operation

Pipelining: increased utilization




$$U_{\text{sender}} = \frac{3L/R}{2*d_{\text{prop}} + L/R} = \frac{.0024}{30.008} = 0.00081$$

3-packet pipelining increases utilization by a factor of 3!

Go-Back-N: sender

- sender: “window” of up to N , consecutive transmitted but unACKed pkts
 - k -bit seq # in pkt header





- *cumulative ACK*: $\text{ACK}(n)$: ACKs all packets up to, including seq # n
 - on receiving $\text{ACK}(n)$: move window forward to begin at $n+1$
- timer for oldest in-flight packet
- $\text{timeout}(n)$: retransmit packet n and all higher seq # packets in window


Go-Back-N: receiver

- ACK-only: always send ACK for correctly-received packet so far, with highest *in-order* seq #
 - may generate duplicate ACKs
 - need only remember `rcv_base`
- on receipt of out-of-order packet:
 - can discard (don't buffer) or buffer: an implementation decision
 - re-ACK pkt with highest in-order seq #

Receiver view of sequence number space:




Go-Back-N in action



Selective repeat

- receiver *individually* acknowledges all correctly received packets
 - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender times-out/retransmits individually for unACKed packets
 - sender maintains timer for each unACKed pkt
- sender window
 - N consecutive seq #s
 - limits seq #s of sent, unACKed packets

Selective repeat: sender, receiver windows



Selective repeat: sender and receiver

sender

data from above:

- if next available seq # in window, send packet

timeout(n):

- resend packet n , restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark packet n as received
- if n smallest unACKed packet, advance window base to next unACKed seq #

receiver

packet n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yet-received packet


packet n in [rcvbase-N,rcvbase-1]

- ACK(n)

otherwise:

- ignore



Selective Repeat in action



Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3



Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3

Q: What relationship is needed between sequence # size and window size to avoid problem in scenario (b)?

window size must be less than or equal to half the size of the sequence number space

sender window
(after receipt)

0 1 2 3 0 1 2
0 1 2 3 0 1 2
0 1 2 3 0 1 2
0 1 2 3 0 1 2
0 1 2 3 0 1 2



- receiver can't see sender side
- receiver behavior identical in both cases!
- something's (very) wrong!

0 1 2 3 0 1 2
0 1 2 3 0 1 2
0 1 2 3 0 1 2

timeout
retransmit pkt0
0 1 2 3 0 1 2

(b) oops!

receiver window
(after receipt)



Transport layer: overview

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- **Connection-oriented transport: TCP**
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- Principles of congestion control
- TCP congestion control

TCP: overview

RFCs: 793, 1122, 2018, 5681, 7323

- **point-to-point:**
 - one sender, one receiver
- **full duplex data:**
 - bi-directional data flow in same connection
 - MSS: maximum segment size
- **cumulative ACKs**
- **pipelining:**
 - TCP congestion and flow control set window size
- **connection-oriented:**
 - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- **flow controlled:**
 - sender will not overwhelm receiver

TCP segment structure

ACK: seq # of next expected byte; A bit: this is an ACK


length (of TCP header)

Internet checksum

C, E: congestion notification

TCP options

RST, SYN, FIN: connection management



segment seq #: counting bytes of data into bytestream (not segments!)

flow control: # bytes receiver willing to accept

data sent by application into TCP socket

TCP sequence numbers, ACKs

Sequence numbers:

- byte stream “number” of first byte in segment’s data

Acknowledgements:


- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-of-order segments

- A: TCP spec doesn’t say, - up to implementor

outgoing segment from sender


source port #	dest port #
sequence number	
acknowledgement number	
	rwnd
checksum	urg pointer



outgoing segment from receiver

source port #	dest port #
sequence number	
acknowledgement number	
	rwnd
checksum	urg pointer

TCP sequence numbers, ACKs



simple telnet scenario

TCP round trip time, timeout

Q: how to set TCP timeout value?

- longer than RTT, but RTT varies!
- *too short*: premature timeout, unnecessary retransmissions
- *too long*: slow reaction to segment loss


Q: how to estimate RTT?

- *SampleRTT*: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- *SampleRTT* will vary, want estimated RTT “smoother”
 - average several *recent* measurements, not just current *SampleRTT*

TCP round trip time, timeout

$$\text{EstimatedRTT} = (1 - \alpha) * \text{EstimatedRTT} + \alpha * \text{SampleRTT}$$

- exponential weighted moving average (EWMA)
- influence of past sample decreases exponentially fast
- typical value: $\alpha = 0.125$



TCP round trip time, timeout

- timeout interval: **EstimatedRTT** plus “safety margin”
 - large variation in **EstimatedRTT**: want a larger safety margin

$$\text{TimeoutInterval} = \text{EstimatedRTT} + 4 * \text{DevRTT}$$



estimated RTT

“safety margin”

- **DevRTT**: EWMA of **SampleRTT** deviation from **EstimatedRTT**:

$$\text{DevRTT} = (1 - \beta) * \text{DevRTT} + \beta * |\text{SampleRTT} - \text{EstimatedRTT}|$$

(typically, $\beta = 0.25$)

TCP Sender (simplified)

event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unACKed segment
 - expiration interval:
TimeOutInterval

event: timeout

- retransmit segment that caused timeout
- restart timer



event: ACK received

- if ACK acknowledges previously unACKed segments
 - update what is known to be ACKed
 - start timer if there are still unACKed segments


TCP Receiver: ACK generation [RFC 5681]

<i>Event at receiver</i>	<i>TCP receiver action</i>
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send <i>duplicate ACK</i> , indicating seq. # of next expected byte

TCP: retransmission scenarios



TCP: retransmission scenarios



TCP fast retransmit


TCP fast retransmit

if sender receives 3 additional ACKs for same data (“triple duplicate ACKs”), resend unACKed segment with smallest seq #

- likely that unACKed segment lost, so don’t wait for timeout



Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!




Transport layer: overview

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- **Connection-oriented transport: TCP**
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- Principles of congestion control
- TCP congestion control


TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?




TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?




TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



flow control: # bytes
receiver willing to accept

Application removing
data from TCP socket
buffers



receiver protocol stack


TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast


Application removing data from TCP socket buffers



receiver protocol stack

TCP flow control


- TCP receiver “advertises” free buffer space in **rwnd** field in TCP header
 - **RcvBuffer** size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust **RcvBuffer**
- sender limits amount of unACKed (“in-flight”) data to received **rwnd**
- guarantees receive buffer will not overflow



TCP flow control

- TCP receiver “advertises” free buffer space in **rwnd** field in TCP header
 - **RcvBuffer** size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust **RcvBuffer**
- sender limits amount of unACKed (“in-flight”) data to received **rwnd**
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept




TCP segment format


TCP connection management

before exchanging data, sender/receiver “handshake”:

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
Socket clientSocket =  
    newSocket("hostname", "port number");
```



```
Socket connectionSocket =  
    welcomeSocket.accept();
```

TCP 3-way handshake

Client state


```
clientSocket = socket(AF_INET, SOCK_STREAM)
```

LISTEN

```
clientSocket.connect((serverName, serverPort))
```

SYNSENT

choose init seq num, x
send TCP SYN msg



SYNbit=1, Seq=x

ESTAB

received SYNACK(x)
indicates server is live;
send ACK for SYNACK;
this segment may contain
client-to-server data

SYNbit=1, Seq=y
ACKbit=1; ACKnum=x+1

ACKbit=1, ACKnum=y+1

Server state

```
serverSocket = socket(AF_INET, SOCK_STREAM)  
serverSocket.bind(('', serverPort))  
serverSocket.listen(1)  
connectionSocket, addr = serverSocket.accept()
```

LISTEN

SYN RCV

choose init seq num, y
send TCP SYNACK
msg, acking SYN

ESTAB

received ACK(y)
indicates client is live

Closing a TCP connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Transport layer: overview

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- **Principles of congestion control**
- TCP congestion control

Principles of congestion control

Congestion:

- informally: “too many sources sending too much data too fast for *network* to handle”
- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!



congestion control:

too many senders,
sending too fast




flow control: one sender
too fast for one receiver



Causes/costs of congestion: scenario 1

Simplest scenario:

- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed




Q: What happens as arrival rate λ_{in} approaches $R/2$?



Causes/costs of congestion: scenario 2



- one router, *finite* buffers
- sender retransmits lost, timed-out packet
 - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
 - transport-layer input includes *retransmissions* : $\lambda'_{in} \geq \lambda_{in}$



Causes/costs of congestion: scenario 2

Idealization: perfect knowledge


- sender sends only when router buffers available



Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge



- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost



Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge



- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost



Causes/costs of congestion: scenario 2

Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender timers can time out prematurely, sending *two* copies, *both* of which are delivered




Causes/costs of congestion: scenario 2

Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending *two* copies, *both* of which are delivered

“costs” of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
 - decreasing maximum achievable throughput




Causes/costs of congestion: scenario 3



- four senders
- multi-hop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ'_{in} increase ?

A: as red λ'_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput $\rightarrow 0$



Causes/costs of congestion: scenario 3




another “cost” of congestion:

- when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!

Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream



Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion *inferred* from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide *direct* feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Transport layer: overview

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- **TCP congestion control**

TCP congestion control: AIMD


- *approach:* senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase

increase sending rate by 1 maximum segment size every RTT until loss detected

Multiplicative Decrease

cut sending rate in half at each loss event



AIMD sawtooth behavior: *probing* for bandwidth

TCP AIMD: more


Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD – a distributed, asynchronous algorithm – has been shown to:
 - optimize congested flow rates network wide!
 - have desirable stability properties

TCP congestion control: details



TCP sending behavior:


- *roughly*: send $cwnd$ bytes, wait RTT for ACKS, then send more bytes

$$\text{TCP rate} \approx \frac{cwnd}{RTT} \text{ bytes/sec}$$

- TCP sender limits transmission: $\text{LastByteSent} - \text{LastByteAcked} \leq cwnd$
- $cwnd$ is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
 - initially **cwnd** = 1 MSS
 - double **cwnd** every RTT
 - done by incrementing **cwnd** for every ACK received
- summary:* initial rate is slow, but ramps up exponentially fast



TCP: detecting, reacting to loss

- loss indicated by timeout:
 - **cwnd** set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - **cwnd** is cut in half window then grows linearly
- TCP Tahoe always sets **cwnd** to 1 (timeout or 3 duplicate acks)


TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?


A: when **cwnd** gets to 1/2 of its value before timeout.

Implementation:

- variable **ssthresh**
- on loss event, **ssthresh** is set to 1/2 of **cwnd** just before loss event




Summary: TCP congestion control




TCP CUBIC

- Is there a better way than AIMD to “probe” for usable bandwidth?
- Insight/intuition:
 - W_{\max} : sending rate at which congestion was detected
 - congestion state of bottleneck link probably (?) hasn't changed much
 - after cutting rate/window in half on loss, initially ramp to W_{\max} *faster*, but then approach W_{\max} more *slowly*




TCP CUBIC

- K: point in time when TCP window size will reach W_{\max}
 - K itself is tunable
- increase W as a function of the *cube* of the distance between current time and K
 - larger increases when further away from K
 - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




TCP and the congested “bottleneck link”

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the *bottleneck link*




TCP and the congested “bottleneck link”

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the *bottleneck link*
- understanding congestion: useful to focus on congested bottleneck link



Delay-based TCP congestion control

Keeping sender-to-receiver pipe “just full enough, but no fuller”: keep bottleneck link busy transmitting, but avoid high delays/buffering



$$\text{measured throughput} = \frac{\text{\# bytes sent in last RTT interval}}{\text{RTT}_{\text{measured}}}$$

Delay-based approach: TCP Vegas

- RTT_{\min} - minimum observed RTT (uncongested path)
- uncongested throughput with congestion window $cwnd$ is $cwnd/\text{RTT}_{\min}$
 - if measured throughput “very close” to uncongested throughput
increase $cwnd$ linearly /* since path not congested */
 - else if measured throughput “far below” uncongested throughput
decrease $cwnd$ linearly /* since path is congested */

Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout (“keeping the just pipe full... ”) while keeping delay low (“...but not fuller”)
- a number of deployed TCPs take a delay-based approach
 - BBR deployed on Google’s (internal) backbone network

Explicit congestion notification (ECN)

TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked *by network router* to indicate congestion
 - *policy* to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)

