



Qubit dynamics under alternating controls: applications in diamond

Clarice D. Aiello's PhD thesis defense, July 25th, 2014

Quantum Engineering Group @ MIT



Qubit dynamics under alternating controls: applications in diamond

Clarice D. Aiello's PhD thesis defense, July 25th, 2014

Quantum Engineering Group @ MIT

Qubit

Controls

Qubit

Quantum
metrology

Qubit

Quantum
metrology

Quantum
control

Qubit

Controls

Quantum
metrology

Quantum
control

Qubit
nitrogen-vacancy
center

Controls
alternate between
discrete values

Quantum
metrology

Quantum
control

Qubit
nitrogen-vacancy
center

Controls
alternate between
discrete values

a flipping of phases

Quantum
metrology

Quantum
control

Qubit
nitrogen-vacancy center

Controls
alternate between
discrete values

a flipping of phases

a flipping of rotation axes

Quantum
metrology

Quantum
control

Qubit
nitrogen-vacancy center

Controls
alternate between
discrete values

a flipping of phases

a flipping of rotation axes

Quantum
metrology

Quantum
control


- 1 The NV center is a remarkable, controllable quantum system**
- 2 A flipping of phases: NV center as a quantum sensor**
 - Rotary-echo magnetometry with a single NV center brings flexibility
 - Real-life applications can benefit from rotary-echo flexibility
- 3 A flipping of rotation axes: NV center as a quantum actuator**
 - A needed detour: the time-optimal control problem
 - NV-mediated driving of a nuclear qubit can be faster, cleaner
- 4 Conclusion**

- 1** The NV center is a remarkable, controllable quantum system
- 2** A flipping of phases: NV center as a quantum sensor
 - Rotary-echo magnetometry with a single NV center brings flexibility
 - Real-life applications can benefit from rotary-echo flexibility
- 3** A flipping of rotation axes: NV center as a quantum actuator
 - A needed detour: the time-optimal control problem
 - NV-mediated driving of a nuclear qubit can be faster, cleaner
- 4** Conclusion

NV center is one of many defects in diamond

500+ naturally occurring defects in diamond!


- vacancy next to substitutional nitrogen
- localized
- also created by irradiation + annealing
- absorbs light and fluoresces



NV center is one of many defects in diamond

500+ naturally occurring defects in diamond!


- vacancy next to substitutional nitrogen
- localized
- also created by irradiation + annealing
- absorbs light and fluoresces



NV center is a *very* special defect in diamond

500+ naturally occurring defects in diamond!


- vacancy next to substitutional nitrogen
- localized
- also created by irradiation + annealing
- absorbs light and fluoresces



NV center is a *very* special defect in diamond

500+ naturally occurring defects in diamond!


- vacancy next to substitutional nitrogen
⇒ energy levels of electronic spin 1
- localized
- also created by irradiation + annealing
- absorbs light and fluoresces



NV center is a *very* special defect in diamond

500+ naturally occurring defects in diamond!


- vacancy next to substitutional nitrogen
⇒ energy levels of electronic spin 1
- localized
⇒ no trapping requirements
- also created by irradiation + annealing
- absorbs light and fluoresces



NV center is a *very* special defect in diamond

500+ naturally occurring defects in diamond!


- vacancy next to substitutional nitrogen
⇒ energy levels of electronic spin 1
- localized
⇒ no trapping requirements
- also created by irradiation + annealing
⇒ engineer properties
- absorbs light and fluoresces



NV center is a *very* special defect in diamond

500+ naturally occurring defects in diamond!


- vacancy next to substitutional nitrogen
⇒ energy levels of electronic spin 1
- localized
⇒ no trapping requirements
- also created by irradiation + annealing
⇒ engineer properties
- absorbs light and fluoresces
⇒ state-dependent fluorescence intensity



NV center is a *very* special defect in diamond

500+ naturally occurring defects in diamond!

- vacancy next to substitutional nitrogen
⇒ energy levels of electronic spin 1
- localized
⇒ no trapping requirements
- also created by irradiation + annealing
⇒ engineer properties
- absorbs light and fluoresces
⇒ state-dependent fluorescence intensity
- very long $T_2 \approx \text{ms at room temperature}$




Tracking individual NV centers:


Tracking individual NV centers:




Tracking individual NV centers: confocal imaging



Tracking individual NV centers: confocal imaging



Tracking individual NV centers: confocal imaging




State-dependent fluorescence is linked to energy levels

non-resolvable
excited states



ground
states




State-dependent fluorescence is linked to energy levels

non-resolvable
excited states



metastable
state




State-dependent fluorescence is linked to energy levels

non-resolvable
excited states



metastable
state *S*




State-dependent fluorescence is linked to energy levels

non-resolvable
excited states



metastable
state



State-dependent fluorescence is linked to energy levels


non-resolvable
excited states




metastable
state




ground
states



State-dependent fluorescence is linked to energy levels



State-dependent fluorescence is linked to energy levels



State-dependent fluorescence is linked to energy levels

non-resolvable
excited states




metastable
state




ground
states



State-dependent fluorescence is linked to energy levels



State-dependent fluorescence is linked to energy levels



State-dependent fluorescence is linked to energy levels


non-resolvable
excited states



metastable
state



ground
states




State-dependent fluorescence is linked to energy levels

non-resolvable
excited states

metastable
state

ground
states




State-dependent fluorescence is linked to energy levels


non-resolvable
excited states

metastable
state


ground
states




State-dependent fluorescence is linked to energy levels




State-dependent fluorescence is linked to energy levels




State-dependent fluorescence is linked to energy levels




State-dependent fluorescence is linked to energy levels




State-dependent fluorescence is linked to energy levels




State-dependent fluorescence is linked to energy levels



State-dependent fluorescence is linked to energy levels




State-dependent fluorescence is linked to energy levels




- after some time, regardless of the NV initial state, ends up in $| 0 \rangle$ 'initialization'

State-dependent fluorescence is linked to energy levels



- after some time, regardless of the NV initial state, ends up in $| 0 \rangle$ 'initialization'
- before that time, state is distinguishable by fluorescence intensity 'read-out'

Single NV state is observed by fluorescence




compare:

unobservable NMR signal from the tiny magnetic moment of a single spin

The NV center can be controlled with photons


The NV center can be controlled with photons

- laser excites NV off-resonantly




The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out




The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels




The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels





The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels




The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels




The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels




The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels
⇒ coherent control






The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels
⇒ coherent control



The NV center can be controlled with photons

- laser excites NV off-resonantly
⇒ initialization & read-out
- microwaves drive resonant transitions between two energy levels
⇒ coherent control



1 The NV center is a remarkable, controllable quantum system

2 A flipping of phases: NV center as a quantum sensor

- Rotary-echo magnetometry with a single NV center brings flexibility
- Real-life applications can benefit from rotary-echo flexibility

3 A flipping of rotation axes: NV center as a quantum actuator

- A needed detour: the time-optimal control problem
- NV-mediated driving of a nuclear qubit can be faster, cleaner

4 Conclusion

- 1** The NV center is a remarkable, controllable quantum system
- 2** A flipping of phases: NV center as a quantum sensor
 - Rotary-echo magnetometry with a single NV center brings flexibility
 - Real-life applications can benefit from rotary-echo flexibility
- 3** A flipping of rotation axes: NV center as a quantum actuator
 - A needed detour: the time-optimal control problem
 - NV-mediated driving of a nuclear qubit can be faster, cleaner
- 4** Conclusion

To measure things better is to understand nature better




better frequencies

To measure things better is to understand nature better



better frequencies




better magnetic fields


To measure things better is to understand nature better



better frequencies



better magnetic fields




better accelerations

To measure things better is to understand nature better



better frequencies



better magnetic fields




better accelerations

To measure things better is to understand nature better



better frequencies

what if...



better magnetic fields




better accelerations

To measure things better is to understand nature better



better frequencies



better magnetic fields



better accelerations


what if...

...the quantity to be measured is way too small?

To measure things better is to understand nature better



better frequencies



better magnetic fields



better accelerations


what if...

- ...the quantity to be measured is way too small?
- ...object causing the quantity to be measured is way too small?

To measure things better is to understand nature better



better frequencies



better magnetic fields



better accelerations

what if...


- ...the quantity to be measured is way too small?
- ...object causing the quantity to be measured is way too small?

⇒ need tiny sensor, able to measure tiny quantities

To measure things better is to understand nature better



better frequencies



better magnetic fields



better accelerations

what if...


- ...the quantity to be measured is way too small?
- ...object causing the quantity to be measured is way too small?

⇒ need tiny sensor, able to measure tiny quantities


here:

sensing tiny magnetic fields with the NV center in diamond


NV magnetometer: principle of operation




NV magnetometer: principle of operation




NV magnetometer: principle of operation




NV magnetometer: principle of operation



NV magnetometer: principle of operation




NV magnetometer: principle of operation




NV magnetometer: principle of operation

Zeeman shift $\Delta \propto B$
(gyro $\gamma_e \sim 2.8\text{MHz/G}$)



NV magnetometer: principle of operation

Zeeman shift $\Delta \propto B$
(gyro $\gamma_e \sim 2.8\text{MHz/G}$)




measure B
↔
measure
detuning from resonance Δ

The tiny NV magnetometer senses tiny magnetic fields

The tiny NV magnetometer senses tiny detunings


The tiny NV magnetometer senses tiny detunings

- nanoscale probe brought to proximity of sample
- senses detunings caused by few or individual spins





The tiny NV magnetometer senses tiny detunings

- nanoscale probe brought to proximity of sample
- senses detunings caused by few or individual spins





The NV has a built-in testbed magnetic field source



- hyperfine with spin-1 ^{14}N , $A \sim 2\text{MHz}$
- drive center resonance (^{14}N in $m_I = 0$), expect 3 detunings:

$$\Delta = \{ b, A \pm b \}, b \text{ detuning from presumed resonance}$$

The NV has a built-in testbed magnetic field source




- hyperfine with spin-1 ^{14}N , $A \sim 2\text{MHz}$
- drive center resonance (^{14}N in $m_I = 0$), expect 3 detunings:

$$\Delta = \{ b, A \pm b \}, b \text{ detuning from presumed resonance}$$

... but what's the best way to measure those detunings?



Benchmark answer: Ramsey spectroscopy



✓ Signal $\sim \cos(t\Delta)$



✗ T_2^* -limited

Alternative answer: Rabi spectroscopy



✓ Signal $\sim \cos(t\Delta)$




✗ T_2^* -limited



✗ Signal $\sim \cos\left(\frac{t\Delta^2}{\Omega}\right)$

✓ T_1 -limited




Our answer: Rotary-echo spectroscopy



- ✓ Signal $\sim \cos(t\Delta)$
- ✗ T_2^* -limited

- ✗ Signal $\sim \cos\left(\frac{t\Delta^2}{\Omega}\right)$
- ✓ T_1 -limited

Our answer: 'RE' spectroscopy




- ✓ Signal $\sim \cos(t\Delta)$
- ✗ T_2^* -limited

- ✗ Signal $\sim \cos\left(\frac{t\Delta^2}{\Omega}\right)$
- ✓ T_1 -limited

Dynamics under RE sequence is now better understood



- NMR origins Solomon, Phys. Rev. **110**, 61 (1958)
- corrects driving field imperfections
- does not correct detunings from resonance ✓
- length of pulse $\sim \theta$



Dynamics under RE sequence is now better understood

- NMR origins Solomon, Phys. Rev. **110**, 61 (1958)



- corrects driving field imperfections
- does not correct detunings from resonance ✓
- length of pulse $\sim \theta$



Dynamics under RE sequence is now better understood

- NMR origins Solomon, Phys. Rev. 110, 61 (1958)

- corrects driving field imperfections
- does not correct detunings from resonance ✓
- length of pulse $\sim \theta$




$$\text{Signal} \simeq \frac{1}{2} \left[1 + \cos^2 \left(\frac{\theta}{2} \right) + \sin^2 \left(\frac{\theta}{2} \right) \cos \left(\frac{2t\Delta}{\theta} \sin \left(\frac{\theta}{2} \right) \right) \cos \left(\frac{\pi t \Omega}{\theta} \right) \right]$$

Dynamics under RE sequence is now better understood

- NMR origins Solomon, Phys. Rev. 110, 61 (1958)

- corrects driving field imperfections
- does not correct detunings from resonance ✓
- length of pulse $\sim \theta$




$$\text{Signal} \simeq \frac{1}{2} \left[1 + \cos^2 \left(\frac{\theta}{2} \right) + \sin^2 \left(\frac{\theta}{2} \right) \cos \left(\frac{2t\Delta}{\theta} \sin \left(\frac{\theta}{2} \right) \right) \cos \left(\frac{\pi t\Omega}{\theta} \right) \right]$$

Dynamics under RE sequence is now better understood

- NMR origins Solomon, Phys. Rev. 110, 61 (1958)

- corrects driving field imperfections
- does not correct detunings from resonance ✓
- length of pulse $\sim \theta$




$$\text{Signal} \simeq \frac{1}{2} \left[1 + \cos^2 \left(\frac{\theta}{2} \right) + \sin^2 \left(\frac{\theta}{2} \right) \cos \left(\frac{2t\Delta}{\theta} \sin \left(\frac{\theta}{2} \right) \right) \cos \left(\frac{\pi t\Omega}{\theta} \right) \right]$$

Sensitivities of RE can be comparable to Ramsey's...

$$\eta = \frac{1}{\gamma_e} \lim_{\Delta \rightarrow 0} \frac{\sigma_S}{\left| \frac{\partial S}{\partial \Delta} \right|} \sqrt{t},$$

for signal S and interrogation time t



(assuming static bath noise)

$$\eta_{Rabi} \sim \frac{\sqrt{2\Omega}}{\gamma_e}$$


$$\eta_{Ram} = \frac{1}{\gamma_e \sqrt{t}}$$

$$\eta_{RE} = \frac{1}{\gamma_e \sqrt{t}} \frac{\theta}{1 - \cos \theta}$$

Sensitivities of RE can be comparable to Ramsey's...

$$\eta = \frac{1}{\gamma_e} \lim_{\Delta \rightarrow 0} \frac{\sigma_S}{\left| \frac{\partial S}{\partial \Delta} \right|} \sqrt{t},$$

for signal S and interrogation time t





(assuming static bath noise)

$$\eta_{Rabi} \sim \frac{\sqrt{2\Omega}}{\gamma_e} \quad \eta_{Ram} = \frac{1}{\gamma_e \sqrt{t}} \quad \eta_{RE} = \frac{1}{\gamma_e \sqrt{t}} \frac{\theta}{1 - \cos \theta} \quad \begin{matrix} \uparrow \text{with } \uparrow \theta \\ \min \text{ for } \theta = 3\pi/4 \end{matrix}$$

Sensitivities of RE can be comparable to Ramsey's...

$$\eta = \frac{1}{\gamma_e} \lim_{\Delta \rightarrow 0} \frac{\sigma_S}{\left| \frac{\partial S}{\partial \Delta} \right|} \sqrt{t},$$

for signal S and interrogation time t





(assuming static bath noise)


Sensitivities of RE can be comparable to Ramsey's...

$$\eta = \frac{1}{\gamma_e} \lim_{\Delta \rightarrow 0} \frac{\sigma_S}{\left| \frac{\partial S}{\partial \Delta} \right|} \sqrt{t},$$

for signal S and interrogation time t





(assuming static bath noise)




Sensitivities of RE can be comparable to Ramsey's...

$$\eta = \frac{1}{\gamma_e} \lim_{\Delta \rightarrow 0} \frac{\sigma_S}{\left| \frac{\partial S}{\partial \Delta} \right|} \sqrt{t},$$

for signal S and interrogation time t




(assuming static bath noise)




...and coherence times are longer, up to T_1

...and coherence times are longer, up to T_1



...and coherence times are longer, up to T_1




⇒ Trade-off: sensitivity \times coherence times

$\uparrow \theta$

η worsens

\uparrow resilience to bath noise

RE is resilient to different types of noise




⇒ Trade-off: sensitivity \times coherence times

$\uparrow \theta$

η worsens

\uparrow resilience to bath noise

RE is resilient to different types of noise




⇒ Trade-off: sensitivity \times coherence times

$\uparrow \theta$

η worsens

\uparrow resilience to bath noise

RE is resilient to different types of noise



⇒ Trade-off: sensitivity \times coherence times


$$\uparrow \theta$$

η worsens

\uparrow resilience to bath noise

\downarrow resilience to driving noise

RE is resilient to different types of noise




⇒ Trade-off: sensitivity \times coherence times

$$\uparrow \theta$$

η worsens

\uparrow resilience to bath noise

\downarrow resilience to driving noise



RE is resilient to different types of noise

⇒ Trade-off: sensitivity \times coherence times




$$\uparrow \theta$$

η worsens

\uparrow resilience to bath noise

\downarrow resilience to driving noise

Choice of θ yields flexibility



✓ Signal $\sim \cos(t\Delta)$

✗ T_2^* -limited




✓ Signal $\sim \cos(\kappa t\Delta)$

✓ intermediate times

✗ Signal $\sim \cos\left(\frac{t\Delta^2}{\Omega}\right)$

✓ T_1 -limited

Choice of θ yields flexibility



✓ Signal $\sim \cos(t\Delta)$

✗ T_2^* -limited

✓ Signal $\sim \cos(\kappa t\Delta)$

✓ intermediate times

✓ choice of θ

✗ Signal $\sim \cos\left(\frac{t\Delta^2}{\Omega}\right)$

✓ T_1 -limited

Fedder et al., Appl. Phys. B 102, 497 (2011)

1 The NV center is a remarkable, controllable quantum system

2 A flipping of phases: NV center as a quantum sensor

- Rotary-echo magnetometry with a single NV center brings flexibility
- Real-life applications can benefit from rotary-echo flexibility

3 A flipping of rotation axes: NV center as a quantum actuator

- A needed detour: the time-optimal control problem
- NV-mediated driving of a nuclear qubit can be faster, cleaner

4 Conclusion

Sensing in variable environments requires flexibility


Maybe...

- ...field from samples under study have different lifetimes


⇒ match RE interrogation time to each particular sample

- ...unknown noise sources


⇒ tune sensor protection by choosing θ accordingly




Nanodomain



Microdomain



Degen, Appl. Phys. Lett. 92, 243111 (2008)




Augustine et al., Neuron 40, 331 (2003)


- 1** The NV center is a remarkable, controllable quantum system
- 2** A flipping of phases: NV center as a quantum sensor
 - Rotary-echo magnetometry with a single NV center brings flexibility
 - Real-life applications can benefit from rotary-echo flexibility
- 3** A flipping of rotation axes: NV center as a quantum actuator
 - A needed detour: the time-optimal control problem
 - NV-mediated driving of a nuclear qubit can be faster, cleaner
- 4** Conclusion

- 1** The NV center is a remarkable, controllable quantum system
- 2** A flipping of phases: NV center as a quantum sensor
 - Rotary-echo magnetometry with a single NV center brings flexibility
 - Real-life applications can benefit from rotary-echo flexibility
- 3** A flipping of rotation axes: NV center as a quantum actuator
 - A needed detour: the time-optimal control problem
 - NV-mediated driving of a nuclear qubit can be faster, cleaner
- 4** Conclusion

Placing the NV into the background



Placing the NV into the background



Grandma, here's what I'm up to

Grandma, here's what I'm up to



Grandma, here's what I'm up to




Grandma, here's what I'm up to




Fast ice-cream delivery... with a **broken** cart?




Fast ice-cream delivery... with a **broken** cart?




Fast ice-cream delivery... with a **broken** cart?



Fast ice-cream delivery... with a **broken** cart?



Fast ice-cream delivery... with a **broken** cart?




Physics equivalent:

Time-optimal qubit transfer with restricted controls


Time-optimal qubit transfer with restricted controls

- qubit state: point on surface of Bloch sphere



Time-optimal qubit transfer with restricted controls


- qubit state: point on surface of Bloch sphere
- experimental controls: rotations around Bloch sphere axes



Time-optimal qubit transfer with restricted controls

- qubit state: point on surface of Bloch sphere
- experimental controls: rotations around Bloch sphere axes

how to steer the state of a qubit...




Time-optimal qubit transfer with restricted controls

- qubit state: point on surface of Bloch sphere
- experimental controls: rotations around Bloch sphere axes

how to steer the state of a qubit...

...as fast as possible, before decoherence kicks in?




Time-optimal qubit transfer with restricted controls

- qubit state: point on surface of Bloch sphere
- experimental controls: rotations around Bloch sphere axes

how to steer the state of a qubit...

...as fast as possible, before decoherence kicks in?
...especially when you cannot take the fastest route?



Time-optimal qubit transfer with restricted controls



- qubit state: point on surface of Bloch sphere
- experimental controls: rotations around Bloch sphere axes

how to steer the state of a qubit...

...as fast as possible, before decoherence kicks in?
...especially when you cannot take the fastest route?

here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two qubit states)



Time-optimal qubit transfer with restricted controls


- qubit state: point on surface of Bloch sphere
- experimental controls: rotations around Bloch sphere axes

how to steer the state of a qubit...

...as fast as possible, before decoherence kicks in?
...especially when you cannot take the fastest route?

here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two qubit states)



Time-optimal qubit transfer with restricted controls



- qubit state: point on surface of Bloch sphere
- experimental controls: rotations around Bloch sphere axes

how to steer the state of a qubit...


...as fast as possible, before decoherence kicks in?
...especially when you cannot take the fastest route?

here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two qubit states)



$$\vec{n}_v \rightarrow \vec{n}_x \rightarrow \vec{n}_v$$




$$\vec{n}_x \rightarrow (\vec{n}_v \rightarrow \vec{n}_x)^2 \rightarrow \vec{n}_v$$

We went further:


Time-optimal unitary synthesis with restricted controls

- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere




Time-optimal unitary synthesis with restricted controls

- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere




here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two unitaries in $SU(2)$, in particular $\mathbb{1} \leftrightarrow U_{\text{goal}}$)



Time-optimal unitary synthesis with restricted controls


- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere



here:


controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two unitaries in $SU(2)$, in particular $\mathbb{1} \leftrightarrow U_{\text{goal}}$)

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for } \min \sum_{i=1}^n |t_i|$$



Time-optimal unitary synthesis with restricted controls

- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere




here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two unitaries in $SU(2)$, in particular $\mathbb{1} \leftrightarrow U_{\text{goal}}$)

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for } \min \sum_{i=1}^n |t_i|$$


rotation around \vec{n}_x : $X(t) \equiv e^{i\sigma_x \frac{t}{2}}$

rotation around \vec{n}_v : $V(t) \equiv e^{i\sigma_v \frac{t}{2}}, \sigma_v = \cos(\alpha)\sigma_x + \sin(\alpha)\sigma_y$



Time-optimal unitary synthesis with restricted controls

- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere




here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two unitaries in $SU(2)$, in particular $\mathbb{1} \leftrightarrow U_{\text{goal}}$)

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for min } \sum_{i=1}^n |t_i|$$


rotation around \vec{n}_x : $X(t) \equiv e^{i\sigma_x \frac{t}{2}}$

rotation around \vec{n}_v : $V(t) \equiv e^{i\sigma_v \frac{t}{2}}, \sigma_v = \cos(\alpha)\sigma_x + \sin(\alpha)\sigma_y$



Time-optimal unitary synthesis with restricted controls

- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere





here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two unitaries in $SU(2)$, in particular $\mathbb{1} \leftrightarrow U_{\text{goal}}$)

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for } \min \sum_{i=1}^n |t_i|$$


rotation around \vec{n}_x : $X(t) \equiv e^{i\sigma_x \frac{t}{2}}$

rotation around \vec{n}_v : $V(t) \equiv e^{i\sigma_v \frac{t}{2}}, \sigma_v = \cos(\alpha)\sigma_x + \sin(\alpha)\sigma_y$



Time-optimal unitary synthesis with restricted controls

- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere




here:

controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two unitaries in $SU(2)$, in particular $\mathbb{1} \leftrightarrow U_{\text{goal}}$)

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for min } \sum_{i=1}^n |t_i|$$


rotation around \vec{n}_x : $X(t) \equiv e^{i\sigma_x \frac{t}{2}}$

rotation around \vec{n}_v : $V(t) \equiv e^{i\sigma_v \frac{t}{2}}, \sigma_v = \cos(\alpha)\sigma_x + \sin(\alpha)\sigma_y$



Time-optimal unitary synthesis with restricted controls

- qubit rotations are parametrized by unitaries $U \in SU(2)$
- unitary U : point on a 3-sphere



here:


controls restricted to rotations around 2 non-parallel axes of the Bloch sphere
(proven to link any two unitaries in $SU(2)$, in particular $\mathbb{1} \leftrightarrow U_{\text{goal}}$)

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for min } \sum_{i=1}^n |t_i|$$




rotation around \vec{n}_x : $X(t) \equiv e^{i\sigma_x \frac{t}{2}}$

rotation around \vec{n}_v : $V(t) \equiv e^{i\sigma_v \frac{t}{2}}, \sigma_v = \cos(\alpha)\sigma_x + \sin(\alpha)\sigma_y$



✓ valid solution regardless of qubit (or satellite!) state



Considered cases: rotation angle t in different domains




Considered cases: rotation angle t in different domains




$$\Rightarrow \forall t \in]0, 2\pi[$$

$$\Rightarrow \forall t \in]-\pi, \pi]$$




Our novel approach to time-optimal control

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for min } \sum_{i=1}^n |t_i|$$




- strategy: if U_{goal} is generated in minimum time, find necessary conditions on the control sequence parameters $\{t_1, t_2 \dots, t_n\}$, and length n (note: n finite, or $n \rightarrow \infty$)
- tools: algebraic properties of concatenations of control rotations
 - I. time-optimal sequences have like subsequences
 - II. unitaries have alternative algebraic decompositions
- accessible to the experimentalist
- as opposed to geometric control




Our novel approach to time-optimal control

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for min } \sum_{i=1}^n |t_i|$$




- strategy: if U_{goal} is generated in minimum time, find necessary conditions on the control sequence parameters $\{t_1, t_2 \dots, t_n\}$, and length n (note: n finite, or $n \rightarrow \infty$)
- tools: algebraic properties of concatenations of control rotations
 - I. time-optimal sequences have like subsequences
 - II. unitaries have alternative algebraic decompositions
- accessible to the experimentalist
- as opposed to geometric control
 - abstract (challenging to find solutions to specific cases)




Our novel approach to time-optimal control

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for min } \sum_{i=1}^n |t_i|$$




- strategy: if U_{goal} is generated in minimum time, find necessary conditions on the control sequence parameters $\{t_1, t_2 \dots, t_n\}$, and length n (note: n finite, or $n \rightarrow \infty$)
- tools: algebraic properties of concatenations of control rotations
 - I. time-optimal sequences have like subsequences
 - II. unitaries have alternative algebraic decompositions
- accessible to the experimentalist
- as opposed to geometric control
 - abstract (challenging to find solutions to specific cases)
 - hard (convolved systems of differential equations)




Our novel approach to time-optimal control

$$U_{\text{goal}} = X(t_n) \cdot \dots \cdot V(t_2) \cdot X(t_1) \cdot \mathbb{1}, \text{ for min } \sum_{i=1}^n |t_i|$$





- strategy: if U_{goal} is generated in minimum time, find necessary conditions on the control sequence parameters $\{t_1, t_2 \dots, t_n\}$, and length n (note: n finite, or $n \rightarrow \infty$)
- tools: algebraic properties of concatenations of control rotations
 - I. time-optimal sequences have like subsequences
 - II. unitaries have alternative algebraic decompositions
- accessible to the experimentalist
- as opposed to geometric control
 - abstract (challenging to find solutions to specific cases)
 - hard (convolved systems of differential equations)
 - typically state-to-state



I. Time-optimal sequences have like subsequences

a 4-subsequence of a time-optimal sequence is time-optimal:



$$U_{\text{goal}} = \dots U^* \dots$$



I. Time-optimal sequences have like subsequences

a 4-subsequence of a time-optimal sequence is time-optimal:


$$U^* = X(t_4) \cdot V(t_3) \cdot X(t_2) \cdot V(t_1)$$



I. Time-optimal sequences have like subsequences


a 4-subsequence of a time-optimal sequence is time-optimal:

$$U^* = X(t_4) \cdot V(t_3) \cdot X(t_2) \cdot V(t_1)$$



perturbing times:


$$U^* + dU^* = X(t_4 + \epsilon_4) \cdot V(t_3 + \epsilon_3) \cdot X(t_2 + \epsilon_2) \cdot V(t_1 + \epsilon_1)$$



I. Time-optimal sequences have like subsequences

a 4-subsequence of a time-optimal sequence is time-optimal:

$$U^* = X(t_4) \cdot V(t_3) \cdot X(t_2) \cdot V(t_1)$$



perturbing times:


$$U^* + dU^* = X(t_4 + \epsilon_4) \cdot V(t_3 + \epsilon_3) \cdot X(t_2 + \epsilon_2) \cdot V(t_1 + \epsilon_1)$$

and imposing:

$$dU^* \approx 0$$

$$dT \equiv \epsilon_4 + \epsilon_3 + \epsilon_2 + \epsilon_1 = 0$$

$$d^2T > 0$$



I. Time-optimal sequences have like subsequences



$$U^* = X(t_4) \cdot V(t_3) \cdot X(t_2) \cdot V(t_1)$$

$$dT = 0$$

$$t_2 = t_3 \equiv t_m$$

from n to
only 3 params!

$$d^2T > 0$$



$$\text{finite } n: \\ t_m > \pi$$

$$n \rightarrow \infty: \\ t_m \rightarrow 0$$



$$\text{finite } n: \\ t_m \text{ bounds} \\ \text{signs} \\ \{++--\}, \\ \{+-+-+\}$$

$$n \rightarrow \infty: \\ t_m \rightarrow 0 \\ \text{signs} \\ \{++++\}, \\ \{+-+--\}$$

II. Unitaries have alternative algebraic decompositions

up to a global phase,



$$U^* = X(t)$$



II. Unitaries have alternative algebraic decompositions

up to a global phase,


$$\begin{aligned} U^* &= X(t) \\ &= V(t^*) \cdot X(2\pi - t) \cdot V(t^*) \end{aligned}$$




II. Unitaries have alternative algebraic decompositions

up to a global phase,

$$\begin{aligned} U^* &= X(t) \\ &= V(t^*) \cdot X(2\pi - t) \cdot V(t^*) \end{aligned}$$




$$t^* = -2 \arccot \left(\cos(\alpha) \tan \left(\frac{t}{2} \right) \right)$$



II. Unitaries have alternative algebraic decompositions

up to a global phase,


$$\begin{aligned} U^* &= X(t) \\ &= V(t^*) \cdot X(2\pi - t) \cdot V(t^*) \end{aligned}$$



$$t^* = -2 \arccot \left(\cos(\alpha) \tan \left(\frac{t}{2} \right) \right)$$

then, compare:


$$|t| \stackrel{?}{>} |2\pi - t| + 2|t^*|$$



II. Unitaries have alternative algebraic decompositions

up to a global phase,

$$\begin{aligned} U^* &= X(t) \\ &= V(t^*) \cdot X(2\pi - t) \cdot V(t^*) \end{aligned}$$




$$t^* = -2 \arccot \left(\cos(\alpha) \tan \left(\frac{t}{2} \right) \right)$$

then, compare:

$$|t| \stackrel{?}{>} |2\pi - t| + 2|t^*|$$


finally, discard non-time-optimal intervals for t



II. Unitaries have alternative algebraic decompositions

up to a global phase, $\forall |\delta| < |t|$,

$$\begin{aligned} U^* &= X(\delta) \cdot V(t) \cdot X(\delta) \\ &= V(\tau) \cdot X(\mu) \cdot V(\tau) \end{aligned}$$




$$\tau = \frac{t}{2} + \delta \cos(\alpha) \left(1 - \cos\left(\frac{t}{2}\right) \right) + \mathcal{O}(\delta^2)$$

$$\mu = 2 \delta \cos\left(\frac{t}{2}\right) + \mathcal{O}(\delta^2)$$




then, compare:

$$2|\delta| + |t| \stackrel{?}{>} 2|\tau| + |\mu|$$

finally, discard non-time-optimal intervals for t






II. Unitaries have alternative algebraic decompositions



$n = 1, 2, 3, 4, 5 \text{ or } \infty$

$$n \leq \left\lfloor \frac{\pi}{\alpha} \right\rfloor + 3$$





II. Unitaries have alternative algebraic decompositions



$n = 1, 2, 3, 4, 5$ or ∞



$$n \leq \lfloor \frac{\pi}{\alpha} \rfloor + 3$$







Boost for numerics of time-optimal unitary synthesis

- novel approach to find time-optimal sequences using alternating controls
- mapping of necessary algebraic properties of time-optimal sequences
- parameter search vastly reduced
- optimization problem → algebraic problem
- results applicable to any system with such restricted controls




Boost for numerics of time-optimal unitary synthesis

- novel approach to find time-optimal sequences using alternating controls
- mapping of necessary algebraic properties of time-optimal sequences
- parameter search vastly reduced
- optimization problem → algebraic problem
- results applicable to any system with such restricted controls




- 1** The NV center is a remarkable, controllable quantum system
- 2** A flipping of phases: NV center as a quantum sensor
 - Rotary-echo magnetometry with a single NV center brings flexibility
 - Real-life applications can benefit from rotary-echo flexibility
- 3** A flipping of rotation axes: NV center as a quantum actuator
 - A needed detour: the time-optimal control problem
 - NV-mediated driving of a nuclear qubit can be faster, cleaner
- 4** Conclusion


Bringing the NV back from the background




Bringing the NV back from the background




Bringing the NV back from the background



Bringing the NV back from the background



Bringing the NV back from the background



NV couples to (naturally occurring) ^{13}C via hyperfine interaction

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$$|0\rangle_{\text{NV}} \rightarrow \mathcal{H}_{\text{HF}} = 0$$

$$|\pm 1\rangle_{\text{NV}} \rightarrow \mathcal{H}_{\text{HF}} \sim \mathcal{A} \cdot S_x I_x + \mathcal{B} \cdot S_x I_y$$

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$$|0\rangle_{\text{NV}} \rightarrow \mathcal{H}_{\text{HF}} = 0$$

$$|\pm 1\rangle_{\text{NV}} \rightarrow \mathcal{H}_{\text{HF}} \sim \mathcal{A} \cdot S_x I_x + \mathcal{B} \cdot S_x I_y$$

\vec{n}_x quantization axis $\parallel \vec{B}_0$

S, I spin operators for NV and ^{13}C

\mathcal{A}, \mathcal{B} iso and anisotropic parts of hyperfine

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$|0\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around \vec{n}_x

$|\pm 1\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around axis between $\vec{n}_x, \vec{n}_y : \vec{n}_v$

\vec{n}_x quantization axis $\parallel \vec{B}_0$

S, I spin operators for NV and ^{13}C


\mathcal{A}, \mathcal{B} iso and anisotropic parts of hyperfine

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$|0\rangle_{\text{NV}} \rightarrow ^{13}\text{C}$ qubit precesses around \vec{n}_x

$|\pm 1\rangle_{\text{NV}} \rightarrow ^{13}\text{C}$ qubit precesses around axis between \vec{n}_x , \vec{n}_y , \vec{n}_v



\vec{n}_x quantization axis $\parallel \vec{B}_0$

S, I spin operators for NV and ^{13}C


\mathcal{A}, \mathcal{B} iso and anisotropic parts of hyperfine

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$|0\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around \vec{n}_x

$|\pm 1\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around axis between \vec{n}_x , \vec{n}_y , \vec{n}_v



\vec{n}_x quantization axis $\parallel \vec{B}_0$

S, I spin operators for NV and ^{13}C

\mathcal{A}, \mathcal{B} iso and anisotropic parts of hyperfine


\Rightarrow switching the NV between $|0\rangle_{\text{NV}} \leftrightarrow |\pm 1\rangle_{\text{NV}}$ can steer the ^{13}C anywhere

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$|0\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around \vec{n}_x

$|\pm 1\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around axis between \vec{n}_x , \vec{n}_y , \vec{n}_v



\vec{n}_x quantization axis $\parallel \vec{B}_0$

S, I spin operators for NV and ^{13}C

\mathcal{A}, \mathcal{B} iso and anisotropic parts of hyperfine

\Rightarrow switching the NV between $|0\rangle_{\text{NV}} \leftrightarrow |\pm 1\rangle_{\text{NV}}$ can steer the ^{13}C anywhere


- NV electronic spin is 'actuator'

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$|0\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around \vec{n}_x

$|\pm 1\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around axis between \vec{n}_x , \vec{n}_y , \vec{n}_v



\vec{n}_x quantization axis $\parallel \vec{B}_0$

S, I spin operators for NV and ^{13}C

\mathcal{A}, \mathcal{B} iso and anisotropic parts of hyperfine

\Rightarrow switching the NV between $|0\rangle_{\text{NV}} \leftrightarrow |\pm 1\rangle_{\text{NV}}$ can steer the ^{13}C anywhere


- NV electronic spin is 'actuator'
- formalism to design fast unitaries for the ^{13}C is ready!

Hyperfine mimics discussed control set for ^{13}C qubit

hyperfine interaction:

$|0\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around \vec{n}_x

$|\pm 1\rangle_{\text{NV}} \rightarrow$ ^{13}C qubit precesses around axis between \vec{n}_x , \vec{n}_y , \vec{n}_v



\vec{n}_x quantization axis $\parallel \vec{B}_0$


S, I spin operators for NV and ^{13}C

\mathcal{A}, \mathcal{B} iso and anisotropic parts of hyperfine

\Rightarrow switching the NV between $|0\rangle_{\text{NV}} \leftrightarrow |\pm 1\rangle_{\text{NV}}$ can steer the ^{13}C anywhere

- NV electronic spin is 'actuator'
- formalism to design fast unitaries for the ^{13}C is ready!
- caveat: only works if hyperfine anisotropic, since $\alpha = \arctan \left(\frac{\mathcal{B}}{\omega_0 \pm \mathcal{A}} \right)$


NV spin switch also changes the ^{13}C Larmor frequency



Larmor frequency if $|0\rangle_{\text{NV}}$: $\omega_0 \equiv \gamma_n B_0$, $\gamma_n \sim 1\text{kHz/G}$

Larmor frequency if $|\pm 1\rangle_{\text{NV}}$: $\omega_{\pm 1} = \sqrt{(\omega_0 \pm \mathcal{A})^2 + \mathcal{B}^2}$

NV spin switch also changes the ^{13}C Larmor frequency




Larmor frequency if $|0\rangle_{\text{NV}}$: $\omega_0 \equiv \gamma_n B_0$, $\gamma_n \sim 1\text{kHz/G}$

Larmor frequency if $|\pm 1\rangle_{\text{NV}}$: $\omega_{\pm 1} = \sqrt{(\omega_0 \pm \mathcal{A})^2 + \mathcal{B}^2}$

introduce a parameter to measure difference in 'evolution speed':

$$\kappa = \frac{\omega_0}{\omega_{\pm 1}} \in [0, 1]$$

NV spin switch also changes the ^{13}C Larmor frequency



Larmor frequency if $|0\rangle_{\text{NV}}$: $\omega_0 \equiv \gamma_n B_0$, $\gamma_n \sim 1\text{kHz/G}$

Larmor frequency if $|\pm 1\rangle_{\text{NV}}$: $\omega_{\pm 1} = \sqrt{(\omega_0 \pm \mathcal{A})^2 + \mathcal{B}^2}$

introduce a parameter to measure difference in 'evolution speed':

$$\kappa = \frac{\omega_0}{\omega_{\pm 1}} \in [0, 1]$$

(my presentation of the control problem assumed $\kappa = 1$;
complete theoretical framework *does* take $\kappa \neq 1$ into account)


Actuator can be faster, cleaner than direct driving of ^{13}C

direct driving of ^{13}C qubit:



- (noisy) radio-frequency photons
- Rabi frequency $\Omega \lesssim 100\text{kHz}$

numerical search of time-optimal actuator solutions:

- $U_{\text{goal}} = Z(\pi)$
- large range of $\{\alpha, \kappa\}$
- real $\{\alpha(B_0), \kappa(B_0)\}$:
pick $B_0 = 500\text{G}$
- comparison with ^{13}C hyperfine data yielded by density functional theory



Actuator beneficial over large ranges of B_0 and distance



- 1** The NV center is a remarkable, controllable quantum system
- 2** A flipping of phases: NV center as a quantum sensor
 - Rotary-echo magnetometry with a single NV center brings flexibility
 - Real-life applications can benefit from rotary-echo flexibility
- 3** A flipping of rotation axes: NV center as a quantum actuator
 - A needed detour: the time-optimal control problem
 - NV-mediated driving of a nuclear qubit can be faster, cleaner
- 4** Conclusion

The past hour

The past hour

- NV center qubit is ideal
for both quantum control and quantum metrology protocols

The past hour

- NV center qubit is ideal
for both quantum control and quantum metrology protocols
- NV center is a very sensitive magnetometer

The past hour

- NV center qubit is ideal
for both quantum control and quantum metrology protocols
- NV center is a very sensitive magnetometer
- rotary-echo magnetometry allows for flexibility
 - can compensate for different scenarios of noise strength and origin
 - suitable choice of pulse length θ

The past hour

- NV center qubit is ideal
for both quantum control and quantum metrology protocols
- NV center is a very sensitive magnetometer
- rotary-echo magnetometry allows for flexibility
 - can compensate for different scenarios of noise strength and origin
 - suitable choice of pulse length θ
- clever use of quantum mechanical techniques
improves real-life applications

The past hour

- NV center qubit is ideal
for both quantum control and quantum metrology protocols
- NV center is a very sensitive magnetometer
- rotary-echo magnetometry allows for flexibility
 - can compensate for different scenarios of noise strength and origin
 - suitable choice of pulse length θ
- clever use of quantum mechanical techniques
improves real-life applications
- NV center is a noise-free actuator


The past hour

- NV center qubit is ideal
for both quantum control and quantum metrology protocols
- NV center is a very sensitive magnetometer
- rotary-echo magnetometry allows for flexibility
 - can compensate for different scenarios of noise strength and origin
 - suitable choice of pulse length θ
- clever use of quantum mechanical techniques
improves real-life applications
- NV center is a noise-free actuator
- actuator protocol can drive a coupled nuclear qubit advantageously


The past hour

- NV center qubit is ideal
for both quantum control and quantum metrology protocols
- NV center is a very sensitive magnetometer
- rotary-echo magnetometry allows for flexibility
 - can compensate for different scenarios of noise strength and origin
 - suitable choice of pulse length θ
- clever use of quantum mechanical techniques
improves real-life applications
- NV center is a noise-free actuator
- actuator protocol can drive a coupled nuclear qubit advantageously
- (analysis made possible via novel approach to time-optimal control)

The future: quantum control and metrology in diamond




The future: quantum control and metrology in diamond



...scale it up!


The future: quantum control and metrology in diamond



...scale it up!

The future: quantum control and metrology in diamond

J. Meijer *et al.*, Appl. Phys. A 83, 321 (2006)



...scale it up!