# CS 305: Computer Networks Fall 2023

**Link Layer** 

Ming Tang

Department of Computer Science and Engineering Southern University of Science and Technology (SUSTech)

# Link layer, LANs: outline

- 6.1 introduction, services
- 6.2 error detection, correction
- 6.3 multiple access protocols
- 6.4 LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS
- 6.5 link virtualization: MPLS
- 6.6 data center networking
- 6.7 a day in the life of a web request

### Link layer: introduction


#### terminology:

Hosts, switches, access points: nodes


 communication channels that connect adjacent nodes along communication path: links

- wired links
- wireless links
- layer-2 packet: frame, encapsulates datagram

*link layer* has responsibility of transferring datagram from one node to *physically adjacent* node over a link



# Link layer: introduction



# Link layer: context

- datagram transferred by different link protocols over different links:
  - e.g., Ethernet on first link, PPP on intermediate links, 802.11 on last link
- each link protocol provides different services
  - e.g., may or may not provide rdt over link

#### transportation analogy:

- trip from SUSTech to Universal Studio
  - metro: SUSTech to SZ North
  - High speed train: SZ North to Beijing West
  - taxi: Beijing West to Universal Studio
- tourist = datagram
- transport segment = communication link
- transportation mode = link layer protocol
- travel agent = routing algorithm

# Link layer services


- framing, link access:
  - encapsulate datagram into frame, adding header, trailer
  - channel access if shared medium
  - "MAC" addresses used in frame headers to identify source, destination
    - different from IP address!
- reliable delivery between adjacent nodes
  - we learned how to do this already (chapter 3)!
  - seldom used on low bit-error link (fiber, some twisted pair)
  - wireless links: high error rates
    - Q: why both link-level and end-end reliability?

# Link layer services (more)


- error detection:
  - errors caused by signal attenuation, noise.
  - receiver detects presence of errors:
    - signals sender for retransmission or drops frame
- error correction:
  - receiver identifies *and corrects* bit error(s) without resorting to retransmission
- half-duplex and full-duplex
  - with half duplex, nodes at both ends of link can transmit, but not at same time

#### Where is the link layer implemented?

- in each and every host
- link layer implemented in "adaptor" (aka network interface card NIC) or on a chip
  - Ethernet card, 802.11 card; Ethernet chipset
  - implements link, physical layer
- attaches into host's system buses
- combination of hardware, software, firmware



### Adaptors communicating



- sending side:
  - encapsulates datagram in frame
  - adds error checking bits, rdt, etc.

- receiving side
  - looks for errors, rdt, flow control, etc.
  - extracts datagram, passes to upper layer at receiving side

# Link layer, LANs: outline


- 6.1 introduction, services
- 6.2 error detection, correction
- 6.3 multiple access protocols
- 6.4 LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS
- 6.5 link virtualization: MPLS
- 6.6 data center networking
- 6.7 a day in the life of a web request

### Error detection and correction

**EDC=** Error Detection and Correction bits

D = Data protected by error checking, may include header fields


- Error detection not 100% reliable!
  - protocol may miss some errors, but rarely
  - larger EDC field yields better detection and correction, but larger overhead



# Parity checking

#### single bit parity:

- detect single bit errors
- Even parity scheme
- Odd parity scheme



#### two-dimensional bit parity:


detect and correct single bit errors

correctable single bit error


<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose ross/interactive/

# Parity checking


10111	0
10101	1
10111 10101 11100	1
11110	0



#### Case 1: a bit is in error.



Case 2: two bits are in error.



#### Case 3: error not detected

10111	0	
10011	1	Not Detected so not Corrected
11010	1	not corrected
11110	0	

Many other cases ...

### Internet checksum (review)

goal: detect "errors" (e.g., flipped bits) in transmitted packet (note: used at transport layer only)

#### sender:

- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

#### receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected.

    But maybe errors

    nonetheless?

#### Cyclic redundancy check

- more powerful error-detection coding
- view data bits, **D**, as a binary number
- choose r+1 bit pattern (generator), G
- goal: choose r CRC bits, R, such that
  - <D,R> exactly divisible by G (modulo 2)
  - receiver knows G, divides <D,R> by G. If non-zero remainder: error detected!


1011 XOR 0101 = 1110

1001 XOR 1101 = 0100

1011 - 0101 = 1110

1001 - 1101 = 0100

- can detect all consecutive bit errors of r bits or less
- widely used in practice (Ethernet, 802.11 WiFi, ATM)



#### Cyclic redundancy check

All CRC calculations are done in modulo-2 arithmetic without carries in addition or borrows in subtraction.

- This means that addition and subtraction are identical, and
- both are equivalent to the bitwise exclusive-or (XOR) of the operands.

```
1011 XOR 0101 = 1110

1001 XOR 1101 = 0100

1011 - 0101 = 1110

1001 - 1101 = 0100
```

```
10001 remainder 101
10011|100100110
10011
10110
10011
101
```

Multiplication and division are the same as in base-2 arithmetic, except that any required addition or subtraction is done without carries or borrows.

### CRC example

← d bits ← r bits →

D: data bits to be sent | R: CRC bits


#### want:

 $D.2^{r}$  XOR R = nG equivalently:

 $D \cdot 2^r = nG XOR R$ equivalently:

if we divide D·2<sup>r</sup> by G, want remainder R to satisfy:

$$R = remainder[\frac{D \cdot 2^r}{G}]$$



<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose ross/interactive/

# Link layer, LANs: outline

- 6.1 introduction, services
- 6.2 error detection, correction
- 6.3 multiple access protocols
- 6.4 LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS
- 6.5 link virtualization: MPLS
- 6.6 data center networking
- 6.7 a day in the life of a web request

#### Multiple access links, protocols

#### two types of "links":

- point-to-point
  - PPP for dial-up access
  - point-to-point link between Ethernet switch, host
- broadcast (shared wire or medium)
  - old-fashioned Ethernet
  - 802.11 wireless LAN



shared wire (e.g., cabled Ethernet)



shared RF (e.g., 802.11 WiFi)



shared RF (satellite)



humans at a cocktail party (shared air, acoustical)

### Multiple access protocols

- single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
  - *collision* if node receives two or more signals at the same time

#### multiple access protocol

- distributed algorithm that determines how nodes share channel,
   i.e., determine which and when node can transmit
- communication about channel sharing must use channel itself!
  - no out-of-band channel for coordination

### An ideal multiple access protocol

given: broadcast channel of rate R bps

#### Desired properties:

- 1. when one node wants to transmit, it can send at rate R.
- 2. when M nodes want to transmit, each can send at average rate R/M
- 3. fully decentralized:
  - no special node to coordinate transmissions
  - no synchronization of clocks, slots
- 4. simple

#### MAC protocols: taxonomy


#### three broad classes:

- channel partitioning
  - divide channel into smaller "pieces" (time slots, frequency, code)
  - allocate piece to node for exclusive use
- random access
  - channel not divided, allow collisions
  - "recover" from collisions
- "taking turns"
  - nodes take turns, but nodes with more to send can take longer turns

#### Channel partitioning MAC protocols: TDMA

#### TDMA: time division multiple access


- access to channel in "rounds"
- each station gets fixed length slot (length = packet transmission time) in each round
- unused slots go idle
- example: 6-station LAN, 1,3,4 have packets to send, slots 2,5,6 idle



#### Channel partitioning MAC protocols: FDMA

#### FDMA: frequency division multiple access

- channel spectrum divided into frequency bands
- each station assigned fixed frequency band
- unused transmission time in frequency bands go idle
- example: 6-station LAN, 1,3,4 have packet to send, frequency bands 2,5,6 idle



#### Channel partitioning: limiations

#### Desired properties:

- 1. (x) when one node wants to transmit, it can send at rate R.
- 3. fully decentralized:
  - no special node to coordinate transmissions
  - no synchronization of clocks, slots
- 4. simple

### Random access protocols

- Random access; if fails, wait for a random time
- two or more transmitting nodes → "collision",
- random access MAC protocol specifies:
  - how to detect collisions
  - how to recover from collisions (e.g., via delayed retransmissions)
- Advantage: when node has packet to send
  - transmit at full channel data rate R.
  - no *a priori* coordination among nodes
- examples of random access MAC protocols:
  - slotted ALOHA
  - ALOHA
  - CSMA, CSMA/CD (Ethernet), CSMA/CA (802.11)

### Slotted ALOHA

#### assumptions:


- all frames same size
- time divided into equal size slots (time to transmit 1 frame)
- nodes start to transmit only slot beginning
- nodes are synchronized
- if 2 or more nodes transmit in slot, all nodes detect collision

#### operation:

when node obtains fresh frame, transmits in next slot

- *if no collision:* node can send new frame in next slot
- *if collision:* node retransmits frame in each subsequent slot with probability p until success

### Slotted ALOHA



#### Pros:

- single active node can continuously transmit at full rate of channel
- highly decentralized: only slots in nodes need to be in sync
- simple

#### Cons:

- collisions, wasting slots
- idle slots
- clock synchronization

### Slotted ALOHA: efficiency

efficiency: long-run fraction of successful slots (many nodes, all with many frames to send)

- suppose: N nodes with many frames to send, each transmits in slot with probability p
- prob that given node has success in a slot =  $p(1-p)^{N-1}$
- prob that *any* node has a success =  $Np(1-p)^{N-1}$

- max efficiency: find  $p^*$  that maximizes  $Np(1-p)^{N-1}$
- for many nodes, take limit of  $Np*(1-p*)^{N-1}$  as N goes to infinity, gives:


 $max\ efficiency = 1/e = 0.37$ 

at best: channel used for useful transmissions 37% of time!



# Pure (unslotted) ALOHA

- unslotted Aloha: simpler, no synchronization
- when frame first arrives
  - transmit immediately
- collision probability increases:
  - frame sent at  $t_0$  collides with other frames sent in  $[t_0-1,t_0+1]$



# Pure ALOHA efficiency

P(success by given node) = P(node transmits)

P(no other node transmits in  $[t_0-1,t_0]$  · P(no other node transmits in  $[t_0-1,t_0]$ 

$$= p \cdot (1-p)^{N-1} \cdot (1-p)^{N-1}$$
$$= p \cdot (1-p)^{2(N-1)}$$

... choosing optimum p and then letting  $n \longrightarrow \infty$ 

$$= 1/(2e) = 0.18$$

even worse than slotted Aloha!

#### CSMA (carrier sense multiple access)

#### **CSMA**: listen before transmit:

- if channel sensed idle: transmit entire frame
- if channel sensed busy, defer transmission

human analogy: don't interrupt others!

#### **CSMA** collisions

- collisions can still occur: propagation delay means two nodes may not hear each other's transmission
- collision: entire packet transmission time wasted
  - distance & propagation delay play role in determining collision probability






t,

### CSMA/CD (collision detection)

#### *CSMA/CD:* CSMA+CD (collision detection)

- collision detection  $\rightarrow$  stop talking:
  - collisions detected within short time
  - colliding transmissions are aborted, reducing channel wastage
- Suitable scenarios:
  - easy in wired LANs: measure signal strengths, compare transmitted, received signals
  - difficult in wireless LANs: received signal strength overwhelmed by local transmission strength
- human analogy: the polite conversationalist

### CSMA/CD (collision detection)



### Ethernet CSMA/CD algorithm

- 1. network adapter (network interface card, NIC) receives datagram from network layer, creates frame
- 2. If NIC senses channel idle, starts frame transmission. If NIC senses channel busy, waits until channel idle, then transmits.
- 3. If NIC transmits entire frame without detecting another transmission, NIC is done with frame!

- 4. If NIC detects another transmission while transmitting, aborts and sends jam signal
- 5. After aborting, NIC enters binary (exponential) backoff:
  - after mth collision, NIC chooses K at random from  $\{0,1,2,...,2^m-1\}$ .
  - NIC waits K·512 bit times, returns to Step 2
  - longer backoff interval with more collisions

# "Taking turns" MAC protocols

#### channel partitioning MAC protocols:

- share channel *efficiently* and *fairly* at high load
- inefficient at low load: delay in channel access, 1/N bandwidth allocated even if only 1 active node!

#### random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead

#### "taking turns" protocols


look for best of both worlds!

- when one node wants to transmit, it can send at rate R.
- when M nodes want to transmit, each can send at average rate R/M

# "Taking turns" MAC protocols

#### polling:

- master node "invites" slave nodes to transmit in turn
- maximum number of frames
- concerns:
  - polling overhead
  - single point of failure (master)




The master node must poll each of the nodes in turn no matter they have frames or not

# "Taking turns" MAC protocols


#### token passing:

- control token passed from one node to next sequentially (fixed order).
- distributed
- concerns:
  - token overhead
  - single point of failure (token)



- if it has some frames to transmit. it holds onto the token;
- otherwise, it immediately forwards the token to the next node.

## Case study: Cable access network



#### **DOCSIS**: data over cable service interface specification

- FDM over upstream, downstream frequency channels
  - Downstream (no multiple access); upstream (collision)
- TDM upstream: some slots assigned, some have contention
  - downstream MAP frame: assigns upstream slots
  - request for upstream slots (and data) transmitted random access (binary backoff) in selected slots


# Summary of MAC protocols

- *channel partitioning*, by time, frequency or code
  - Time Division, Frequency Division
- random access (dynamic),
  - ALOHA, S-ALOHA, CSMA, CSMA/CD
  - carrier sensing: easy in some technologies (wire), hard in others (wireless)
  - CSMA/CD used in Ethernet
  - CSMA/CA used in 802.11
- taking turns
  - polling from central site
  - token passing

# Link layer, LANs: outline

- 6.1 introduction, services
- 6.2 error detection, correction
- 6.3 multiple access protocols
- 6.4 LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS
- 6.5 link virtualization: MPLS
- 6.6 data center networking
- 6.7 a day in the life of a web request

## **LANs**



Because these switches operate at the link layer,


- don't recognize network-layer addresses
- don't use routing algorithms like RIP or OSPF to determine paths through switches

## MAC addresses and ARP

- 32-bit IP address:
  - network-layer address for interface
  - used for layer 3 (network layer) forwarding
- MAC (or LAN or physical or Ethernet) address:
  - Adapter (network interface) rather than host or routers
  - Link-layer switches do NOT have MAC addresses
  - function: used "locally" to get frame from one interface to another physically-connected interface (same network, in IP-addressing sense)
  - 48 bit MAC address (for most LANs) burned in NIC ROM, also sometimes software settable; no two adapters have the same address
  - e.g.: 1A-2F-BB-76-09-AD hexadecimal (base 16) notation (each "numeral" represents 4 bits)

## LAN addresses and ARP

each adapter on LAN has unique *LAN* address



# LAN addresses (more)


- MAC address allocation administered by IEEE
- manufacturer buys portion of MAC address space (to assure uniqueness)
- analogy:
  - MAC address: like ID Number
  - IP address: like postal address
- MAC flat address
  - can move LAN card from one LAN to another
- IP hierarchical address
  - address depends on IP subnet to which node is attached

## LAN addresses (more)

- an adapter sends a frame to some destination adapter,
  - inserts the destination adapter's MAC address into the frame and then sends the frame into the LAN
- an adapter receive a frame
  - If there is a match, extracts the enclosed datagram and passes the datagram up the protocol stack;
  - If there isn't a match, discards
- MAC broadcast address FF-FF-FF-FF-FF

## ARP: address resolution protocol

Question: how to determine interface's MAC address, knowing its IP address?



#### $ARP: IP \rightarrow MAC$

 Resolve addresses only for interfaces on the same subnet

ARP table: each IP node (host, router) on LAN has table

IP/MAC address mappings for some LAN nodes:

< IP address; MAC
address; TTL>


• TTL (Time To Live): time after which address mapping will be forgotten (typically 20 min)

## ARP protocol: same LAN


- A wants to send datagram to B
  - B's MAC address not in A's ARP table.
- A broadcasts ARP query packet, containing B's IP address
  - ARP packet: sending IP and MAC, receiving IP and MAC
  - destination MAC address = FF-FF-FF-FF-FF
  - all nodes on LAN receive ARP query
- B receives ARP packet, replies to A with its (B's) MAC address
  - frame sent to A's MAC address (unicast)
- A caches (saves) IP-to-MAC address pair in its ARP table until information becomes old (times out)
- ARP is "plug-and-play":
  - nodes create their ARP tables without intervention from net administrator

#### walkthrough: send datagram from A to B via R


- focus on addressing at IP (datagram) and MAC layer (frame)
- assume A knows B's IP address
- assume A knows IP address of first hop router, R (how?)
- assume A knows R's MAC address (how?)




- A creates IP datagram with IP source A, destination B
- A creates link-layer frame with R's MAC address as destination address, frame contains A-to-B IP datagram




- frame sent from A to R
- frame received at R, datagram removed, passed up to IP




- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram



- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram



- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram



<sup>\*</sup> Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose\_ross/interactive/

# Link layer, LANs: outline

- 6.1 introduction, services
- 6.2 error detection, correction
- 6.3 multiple access protocols
- 6.4 LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS
- 6.5 link virtualization: MPLS
- 6.6 data center networking
- 6.7 a day in the life of a web request