LAB 04

Working with Data related Operator and Directives, Addressing



STUDENT NAME	ROLL NO SEC
	LAB ENGINEER'S SIGNATURE & DATE
MARKS AWARDED: /	
NATIONAL UNIVERSITY OF COMPU (NUCES), F	

Aashir Mehboob, Amin Sadiq,Qurat ain, M Kariz

Lab Session 04: Working with Data Related Operators and Directives, Addressing

OBJECTIVES:

- Observing effect of Arithmetic Instructions on Flag Register
- Direct-offset operands
- OFFSET operator
- PTR operator
- TYPE operator
- LENGTHOF operator
- SIZEOF operator
- Indirect operands
- Indexed operands

Effect of Arithmetic Instructions on Flag Registers

- Status flags are updated to indicate certain properties of the result
- Once a flag is set, it remains in that state until another instruction that affects the flags is executed

Z-Zero Flag:

The Zero flag is set when the result of an operation produces zero in the destination operand.

```
mov cx,1
sub cx,1
                     ; CX = 0, ZF = 1
mov ax, 0FFFFh
inc ax
                     ; AX = 0, ZF = 1
inc ax
                     ; AX = 1, ZF = 0
```

Remember...

- A flag is set when it equals 1.
- A flag is clear when it equals 0.

C-Carry Flag:

This flag is set, when there is a carry out of MSB in case of addition and borrow in case of subtraction.

The Carry flag is set when the result of an operation generates an unsigned value that is



out of range (too big or too small for the destination operand).

```
mov al,0FFh
add al,1 ; CF = 1, AL = 00
; Try to go below zero:

mov al,0
sub al,1 ; CF = 1, AL = FF
```

S-Sign Flag:

This flag indicates the sign of the result of an operation. A 0 for positive number and 1 for a negative number.

mov	AL, 15	mov	AL,15	
add	AL,97	sub	AL,97	
clears the sign flag as		sets the sign flag as		
the result is 112		the result is -82		
(or 0111000 in binary)		(or 10101110 in binary)		

AC-Auxilary Carry Flag:

This flag is set, if there is a carry from the lowest nibble, i.e., bit three during addition, or borrow for the lowest nibble, i.e. bit three, during subtraction.

Suppose we add 1 to 0Fh. The sum (10h) contains a 1 in bit position 4 that was carried out of bit position 3:

```
mov al,0Fh add al,1 ; AC = 1
```

P Parity Flag:

The Parity flag (PF) is set when the least significant byte of the destination has an even number of 1 bits. The following ADD and SUB instructions alter the parity of AL:



```
mov al,10001100b
add al,00000010b
                                ; AL = 10001110, PF = 1
sub al,10000000b
                                ; AL = 00001110, PF = 0
```

O-Over flow Flag:

The Overflow flag is set when the result of a signed arithmetic operation over-flows or underflows the destination operand. For example, the largest possible integer signed byte value is

+127; adding 1 to it causes overflow:

```
mov al, +127
add al,1
                                 ; OF = 1
```

Similarly, the smallest possible negative integer byte value is 128. Subtracting 1 from it causes underflow. The destination operand value does not hold a valid arithmetic result, and the Over- flow flag is set:

Direct-offset Operands:

You can add a displacement to the name of a variable, creating a direct-offset operand. Example:

```
.data
                        BYTE
arrayB
10h,20h,30h,40h,50h
                       arrayW
WORD 100h,200h,300h
.code
```

mov al, arrayB ; AL = 10hmov al,[arrayB+1] ; AL = 20h; AX = 100hmov ax, arrayW mov ax,[arrayW+2] ; AX = 200h

Similarly, the second element in a doubleword array is 4 bytes beyond the first one.



DATA-RELATED OPERATORS AND DIRECTIVES

OFFSET Operator:

The OFFSET operator returns the offset of a data label.

Syntax:

MOV reg32, OFFSET mem ; reg32 points to count

Example:

```
.data
bVal BYTE?
wVal WORD?
dVal DWORD?
```

If bVal is located at offset 00404000h, we would get:

mov esi, OFFSET bval ; ESI = mov esi, OFFSET wVal ; ESI = mov esi, OFFSET dVal ; ESI = mov esi, OFFSET dVal2 ; ESI =

PTR Operator:

We can use the PTR operator to override the declared size of an operand. Note PTR must be used in combination with one of the standard assembler data types.

For example, that we would like to move the lower 16 bits of a doubleword variable named myDouble into AX. The assembler will not permit the following move because the operand sizes do not match:

```
.data
myDouble DWORD 12345678h
.code
mov ax, myDouble ; error
```

But the WORD PTR operator makes it possible to move the low-order word (5678h) to AX:

mov ax, word ptr myDouble ; AX = 5678H



```
and higher word (1234h) to AX:
```

```
mov dx, word ptr myDouble+2
                                    DX = 1234H
```

Moving Smaller Values into Larger Destinations

We might want to move two smaller values from memory to a larger destination operand. In the next example, the first word is copied to the lower half of EAX and the second word is copied to the upper half.

The DWORD PTR operator makes this possible:

```
.data
wordList WORD 5678h, 1234h
.code
mov eax, DWORD PTR wordList
                                                    ; EAX = 12345678h
```

TYPE Operator:

The TYPE operator returns the size, in bytes, of a single element of a variable.

Syntax:

```
MOV reg16, TYPE mem
```

Example 1:

```
.data
var1 BYTE?
                  ; TYPE var1 = 1
var2 WORD?
                  ; TYPE var2 =
2 var3 DWORD?
                   ; TYPE var3
= 4 var4 QWORD?; TYPE var4
= 8
```

Example 2:

.data



```
var1 BYTE 20h
        WORD
var2
1000h
           var3
DWORD?
var4 BYTE 10, 20, 30, 40, 50
msg BYTE 'File not found', 0
.code
mov ax, type var1
                          AX = 0001
                          ; AX = 0002
mov ax, type var2
                          : AX = 0004
mov ax, type var3
mov ax, type var4
                          ; AX = 0001
                          AX = 0001
mov ax, type msg
```

LENGTHOF Operator:

The LENGTHOF operator counts the number of individual elements in a variable that has been defined using DUP.

Syntax:

MOV reg16, LENGTHOF mem

Example:

```
.data
val1 WORD 1000h
val2 SWORD 10, 20, 30
array WORD 10 DUP(?),0
array2 WORD 5 DUP(3 DUP(0))
message BYTE 'File not found', 0

.code
mov ax, LENGTHOF val1 ;AX =1
mov ax, LENGTHOF val2 ;AX =3
mov ax, LENGTHOF array ; AX = 11 mov
ax, LENGTHOF array2 ; AX = 15 mov ax,
LENGTHOF message ;AX=15
```

SIZEOF Operator:

The SIZEOF operator returns the number of bytes an array takes up. It is similar in effect to multiplying LENGTHOF with TYPE.

Syntax:



MOV reg16/32, SIZEOF mem

Example:

.data

intArray WORD 32 DUP(0)

.code

mov eax, SIZEOF int Array

; EAX = 64

Indirect Operands

In protected mode, an indirect operand can be any 32-bit general-purpose register (EAX, EBX, ECX, EDX, ESI, EDI, EBP, and ESP) surrounded by brackets. The register is assumed to contain the address of some data.

Example:

.data

byteVal BYTE 10h

.code

mov esi,OFFSET byteVal

mov al,[esi]

If the destination operand uses indirect addressing, a new value is placed in memory at the location pointed to by the register.

mov [esi],bl

Using PTR with Indirect Operands

inc [esi] ; error: operand must have size

; AL = 10h

The assembler does not know whether ESI points to a byte, word, doubleword, or some other size. The PTR operator confirms the operand size:

inc BYTE PTR [esi]

Arrays

Indirect operands are ideal tools for stepping through arrays.

Example:

.data



```
.code
mov esi,OFFSET arrayB
mov al,[esi]; AL = 10h
inc esi
mov al,[esi]; AL = 20h

If we use an array of 16-bit integers, we add 2 to ESI to address each subsequent array element.
.data
arrayW WORD 1000h,2000h,3000h
.code
mov esi,OFFSET arrayW
mov ax,[esi]; AX = 1000h
add esi,2
mov ax,[esi]; AX = 2000h

If we use an array of 32-bit integers, we add 4 to ESI to address each subsequent array element.
```

Indexed Operands

arrayB BYTE 10h,20h,30h

An indexed operand adds a constant to a register to generate an effective address. Any of the 32-bit general-purpose registers may be used as index registers.

```
SYNTAX:
```

```
constant [ reg32 ] ; reg32 can be any of the 32-bit general registers

[ constant + reg32 ]

EXAMPLE:
.data
arrayB BYTE 20, 40, 60, 80
.code
```



```
mov esi, 1
mov al, arrayB[esi]
inc esi
mov al, arrayB[esi]
mov esi, 3
mov al, [arrayB + esi]
Adding Displacements: The second type of indexed addressing combines a register with a constant
offset. The index register holds the base address of an array.
INCLUDE Irvine32.inc
.data
arrayW WORD 1000h,2000h,3000h
.code
main PROC
mov eax,0
mov ebx,0
mov ecx,0
mov esi,OFFSET arrayW
mov ax, [esi]; AX = 1000h
mov bx,[esi+2]; AX = 2000h
mov cx, [esi+4]; AX = 3000h
```

Scale Factors in Indexed Operands

Indexed operands must take into account the size of each array element when calculating offsets.

SYNTAX:



```
constant [ reg32 * TYPE constant]
EXAMPLE:
INCLUDE Irvine32.inc
.data
arrayW WORD 1000h, 2000h, 3000h, 4000h
.code
main PROC
mov eax,0
mov ebx,0
mov ecx.0
mov esi, 1
mov ax, arrayW[esi * TYPE arrayW]
mov esi, 2
mov bx, arrayW[esi * TYPE arrayW]
mov esi, 3
mov cx, arrayW[esi * TYPE arrayW]
call DumpRegs
```

Exercises:

- 1. Declare a 32-bit signed integer val1 and initialize it with the eight thousand. If val1 is incremented by 1 using the ADD instruction, what will be the values of the Carry and Sign flags?
- 2. Write down the values of the Carry, Sign, Zero, and Overflow flags after each instruction has executed:

```
mov ax,7FF0h
add al.10h
                  : a. CF = SF = ZF = OF =
add ah,1
                  ; b. CF = SF = ZF = OF =
                  ; c. CF = SF = ZF = OF =
add ax,2
```

- 3. Initialize a double word array consisting of elements 8, 5, 1, 2, 6. Sort the given array in ascending order directly with the help of registers. Use direct-offset addressing to access the elements.
- 4. Use following array declarations:

```
arrayB BYTE 10, 20, 30
arrayW WORD 150, 250, 350
arrayD DWORD 600, 1200, 1800
```

Now initialize three double word variables SUM1, SUM2, SUM3 and perform following operations (expressed in pseudo-code here):

```
SUM1 = arrayB[0] + arrayW[0] + arrayD[0]
SUM2 = arrayB[1] + arrayW[1] + arrayD[1]
SUM3 = arrayB[2] + arrayW[2] + arrayD[2]
```

5. Initialize two arrays:

```
array1 BYTE 10, 20, 30, 40
array2 BYTE 4 DUP (?)
```

Copy elements of array1 into array2 in reverse order using either indirect addressing or direct-offset addressing.

- 6. Subtract an array of 5 doublewords using indirect operands.
- 7. Use following array declarations:

```
arrayB BYTE 60, 70, 80
arrayW WORD 150, 250, 350
arrayD DWORD 600, 1200, 1800
```

For each array, add its 1st and last element using scale factors and display the result in a separate register.

