Arktos and Mizar Single Node Installation Guide

Date: 3 Jan 2022

Introduction

This document is intended for new users to install the Arktos platform with Mizar as the underlying network technology.

Installation Steps

Prepare lab machine, the preferred OS is **Ubuntu 18.04**. If you are using AWS, the recommended instance size is t2.2xlarge and the storage size is 128GB or more

cd

git clone https://github.com/CentaurusInfra/mizar.git

cd mizar

chmod 755 setup-machine-arktos.sh

./setup-machine-arktos.sh

```
ubuntu@ip-172-31-25-250:~$ cd
ubuntu@ip-172-31-25-250:~$ git clone https://github.com/CentaurusInfra/mizar.git
Cloning into 'mizar'...
remote: Enumerating objects: 6756, done.
remote: Counting objects: 100% (978/978), done.
remote: Compressing objects: 100% (567/567), done.
remote: Total 6756 (delta 575), reused 713 (delta 390), pack-reused 5778
Receiving objects: 100% (6756/6756), 11.53 MiB | 17.71 MiB/s, done.
Resolving deltas: 100% (4500/4500), done.
ubuntu@ip-172-31-25-250:~$ cd mizar
ubuntu@ip-172-31-25-250:~/mizar$ chmod 755 setup-machine-arktos.sh
ubuntu@ip-172-31-25-250:~/mizar$ chmod 755 setup-machine-arktos.sh
Setup: Install go (currently limited to version 1.13.9)
Hit:1 http://us-west-2.ec2.archive.ubuntu.com/ubuntu
bionic InRelease
Hit:2 http://us-west-2.ec2.archive.ubuntu.com/ubuntu
bionic-updates InRelease
Hit:3 http://us-west-2.ec2.archive.ubuntu.com/ubuntu
bionic-backports InRelease
Hit:4 http://security.ubuntu.com/ubuntu
Bionic-security InRelease
Reading package lists...
Reading package lists...
Reading dependency tree...
Reading state information...
```

The lab machine will be rebooted once the above script is completed, you will be automatically logged out of the lab machine.

- Log onto your lab machine, then run bootstrap.sh script from the Mizar project folder to bootstrap your lab machine.
- Once bootstrap is completed, you can then compile Mizar. Make sure to run these in sudo mode:

```
root@ip-172-31-25-250:/home/ubuntu/mizar# sudo bash bootstrap.sh

NOTE: This script will reboot the system if you opt to allow kernel update.

If reboot is not required, it will log you out and require re-login for new permissions to take effect.

Hit:1 http://us-west-2.ec2.archive.ubuntu.com/ubuntu bionic InRelease

Hit:2 http://us-west-2.ec2.archive.ubuntu.com/ubuntu bionic-updates InRelease

Hit:3 http://us-west-2.ec2.archive.ubuntu.com/ubuntu bionic-backports InRelease

Hit:4 http://security.ubuntu.com/ubuntu bionic-security InRelease

Reading package lists... Done

Reading package lists... Done

Reading state information... Done

Note, selecting 'python-scapy' instead of 'scapy'

build-assential is already the pagest version (12 Aubuntu1)
```

cd ~/mizar

sudo su

make

Install grpcio tools:

python3 -m pip install --user grpcio-tools

make

Build arktos-network-controller (as it is not part of arktos-up.sh yet)

cd \$HOME/go/src/k8s.io/arktos

sudo ./hack/setup-dev-node.sh

make all WHAT=cmd/arktos-network-controller

```
root@ip-172-31-25-250:/home/ubuntu/mizar# cd $HOME/go/src/k8s.io/arktos bash: cd: /root/go/src/k8s.io/arktos: No such file or directory root@ip-172-31-25-250:/home/ubuntu/mizar# sudo ./hack/setup-dev-node.sh sudo: ./hack/setup-dev-node.sh: command not found root@ip-172-31-25-250:/home/ubuntu/mizar# sudo su ubuntu ubuntu@ip-172-31-25-250:/mizar$ cd $HOME/go/src/k8s.io/arktos ubuntu@ip-172-31-25-250://go/src/k8s.io/arktos$ sudo ./hack/setup-dev-node.sh The script is to help install prerequisites of Arktos development environment on a fresh Linux installation.

It's been tested on Ubuntu 16.04 LTS and 18.04 LTS. Update apt.

Hit:1 http://us-west-2.ec2.archive.ubuntu.com/ubuntu bionic InRelease Hit:2 http://us-west-2.ec2.archive.ubuntu.com/ubuntu bionic-updates InRelease Hit:3 http://us-west-2.ec2.archive.ubuntu.com/ubuntu bionic-backports InRelease Hit:4 http://security.ubuntu.com/ubuntu bionic-security InRelease Reading package lists... Done

Building dependency tree

Reading state information... Done

7 packages can be upgraded. Run 'apt list --upgradable' to see them.

Install docker.

Reading package lists... Done

Building dependency tree
```

Also, please ensure the hostname and its ip address in /etc/hosts. For instance, if the hostname is ip-172-31-25-250, ip address is 172.31.25.250:

```
127.0.0.1 localhost
172.31.25.250 ip-172-31-25-250
```

```
127.0.0.1 localhost
172.31.25.250 ip-172-31-25-250

# The following lines are desirable for IPv6 capable hosts
::1 ip6-localhost ip6-loopback
fe00::0 ip6-localnet
ff00::0 ip6-mcastprefix
ff02::1 ip6-allnodes
ff02::2 ip6-allrouters
ff02::3 ip6-allhosts
~
~
~
~
~
~
~
~
~
~
~
~
~
```

Replace the Arktos containerd:

cd \$HOME/mizar

sudo bash replace-containerd.sh

```
ubuntu@ip-172-31-25-250:~/go/src/k8s.io/arktos$ cd $HOME/mizar
ubuntu@ip-172-31-25-250:~/mizar$ ./replace-containerd.sh
bash: ./replace-containerd.sh: Permission denied
ubuntu@ip-172-31-25-250:~/mizar$ sudo ./replace-containerd.sh
sudo: ./replace-containerd.sh: command not found
ubuntu@ip-172-31-25-250:~/mizar$ ls
CODE_OF_CONDUCT.md README.md cli cov go.mod kernelupdate.sh
CONTRIBUTING.md appspec.yml cluster.yaml deploy-mizar.sh go.sum kind-setup.sh
LICENSE bootstrap.sh cmd docs install lcov
Makefile build core etc k8s lib
ubuntu@ip-172-31-25-250:~/mizar$ sudo bash replace-containerd.sh
ubuntu@ip-172-31-25-250:~/mizar$
```

Before deploying Mizar, you will need first start up Arktos API server:

cd \$HOME/go/src/k8s.io/arktos

./hack/arktos-up.sh

```
ubuntu@ip-172-31-25-250:~/mizar$ cd $HOME/go/src/k8s.io/arktos
ubuntu@ip-172-31-25-250:~/go/src/k8s.io/arktos$ ./hack/arktos-up.sh
DBG: Flannel CNI plugin will be installed AFTER cluster is up
DBG: effective feature gates AllAlpha=false,WorkloadInfoDefaulting=true,QPSDoubleGCController=true,QPSDoubleRSControlle
DBG: effective disabling admission plugins
DBG: effective default network template file is /home/ubuntu/go/src/k8s.io/arktos/hack/testdata/default-flat-network.tm
DBG: kubelet arg RESOLV_CONF is /run/systemd/resolve/resolv.conf
WARNING: The kubelet is configured to not fail even if swap is enabled; production deployments should disable swap.
WARNING: This script MAY be run as root for docker socket / iptables functionality; if failures occur, retry as root.
cni plugin is bridge; arktos will use bridge to provision pod network
Ensuring firewall to allow traffic forward by default
-P FORWARD DROP
-P FORWARD DROP
-P FORWARD ACCEPT
Ensuring minimum cni plugin installation...
installing cni plugin binaries
```

```
Logs:
//tmp/kube-apiserver0.log
//tmp/kube-controller-manager.log

//tmp/kube-proxy.log
//tmp/kube-scheduler.log
//tmp/kube-scheduler.log
//tmp/kube-scheduler.log
//tmp/kube-scheduler.log
//tmp/kube-scheduler.log

To start using your cluster, you can open up another terminal/tab and run:
export KUBECONFIG=/var/run/kubernetes/admin.kubeconfig

or
export KUBECONFIG=/var/run/kubernetes/adminN(N=0,1,...).kubeconfig
cluster/kubectl.sh

Alternatively, you can write to the default kubeconfig:
export KUBERNETES_PROVIDER=local
cluster/kubectl.sh config set-cluster local --server=https://ip-172-31-25-25g:6443 --certificate-authority=/var/run/kubernetcluster/kubectl.sh config set-credentials myself --client-key=/var/run/kubernetes/client-admin.key --client-certificate=/var cluster/kubectl.sh config set-context local --cluster=local --user=myself
cluster/kubectl.sh config use-context local
cluster/kubectl.sh config use-context local
cluster/kubectl.sh config use-context local
cluster/kubectl.sh config use-context local
```

Deploy Mizar. Open a new terminal window, and run:

cd \$HOME/mizar

./deploy-mizar.sh

```
ubuntu@ip-172-31-25-250:~/go/src/k8s.io/arktos$ cd $HOME/mizar
ubuntu@ip-172-31-25-250:~/mizar$ ./deploy-mizar.sh
[common:check_cluster_ready] Checking cluster readyness by getting node status.
Kubernetes master is running at http://localhost:8080
KubeDNS is running at http://localhost:8080/api/v1/tenants/system/namespaces/kube-system/services/kube-dr
To further debug and diagnose cluster problems, use 'kubectl cluster-info dump'.
customresourcedefinition.apiextensions.k8s.io/bouncers.mizar.com created
customresourcedefinition.apiextensions.k8s.io/dividers.mizar.com created
customresourcedefinition.apiextensions.k8s.io/endpoints.mizar.com created
customresourcedefinition.apiextensions.k8s.io/subnets.mizar.com created
customresourcedefinition.apiextensions.k8s.io/subnets.mizar.com created
customresourcedefinition.apiextensions.k8s.io/ypcs.mizar.com created
custo
```

Once your arktos server and Mizar are running. To verify, you can open a new terminal and run kubect1 get nodes, you should see a node running with the name starts with "IP" followed by the private IP address of your lab machine.

```
ubuntu@ip-172-31-25-250:~/mizar$ kubectl get nodes

NAME STATUS ROLES AGE VERSION

ip-172-31-25-250 Ready <none> 8m30s v0.9.0
```

You also want make sure the default kubernetes bridge network configuration file is deleted:

sudo ls /etc/cni/net.d

sudo rm /etc/cni/net.d/bridge.conf

Start Arktos network controller. From a new terminal window, run:

cd \$HOME/go/src/k8s.io/arktos

where the kube-apiserver-ip is your lab machine's private ip address

ubuntu@ip-172-31-25-259:~/go/src/k8s.io/arktos\$./_output/local/bin/linux/amd64/arktos-network-controller --kubeconfig=/var/run/kubernetes/admin.kubeconfig -server-ip-172.31.25.250
1013 06:35:40.466832 3447 controller.go:92] starting flat network controller
10103 06:35:40.466939 3447 controller.go:278] Event(v1.0bjectReference{Kind:"Network", Namespace:"", Name:"default", UID:"7ce8f8a3-bdd9-42a0-8e03-7ac92d3bf90b",
10103 06:35:40.567199 3447 event.go:278] Event(v1.0bjectReference{Kind:"Network", Namespace:"", Name:"default", UID:"7ce8f8a3-bdd9-42a0-8e03-7ac92d3bf90b",
10103 06:35:40.567199 3447 event.go:2783 Event(v1.0bjectReference{Kind:"Network", Namespace:"", Name:"default", UID:"7ce8f8a3-bdd9-42a0-8e03-7ac92d3bf90b",
10103 06:35:40.567199 3447 event.go:2783 bdd9-42a0-8e03-7ac92d3bf90b",
10103 06:35:40.567199 3447 event.go: