

IT Admin Guide to IMDSPlus-PAMS 26.1.0.0 (64-bit) Prerequisites

Required Microsoft Runtime Components

This application depends on several Microsoft-provided runtime components that must be installed on the target workstation before launch. These components are standard Microsoft redistributables commonly used across enterprise Windows environments:

1. Visual C++ Redistributable (x86 – 32-bit)

What it is: Runtime libraries for 32-bit applications

What it's for: Although Microsoft OLE DB Driver 19 (x64) installs both 64-bit and 32-bit driver binaries, the x64 installer of the C++ Redistributable does not install 32-bit runtime libraries. The x86 C++ Redistributable must be installed separately to provide required 32-bit runtime dependencies that the x64 OLE DB Driver needs.

File: `vc_redist.x86.exe` (~13 MB)

Reference: [Microsoft Learn - Download OLE DB Driver](#)

2. Visual C++ Redistributable (x64 – 64-bit)

What it is: Runtime libraries for 64-bit applications

What it's for: Provides the 64-bit runtime environment required by MS OLE DB Driver.

File: `vc_redist.x64.exe` (~14 MB)

3. Microsoft OLE DB Driver 19 for SQL Server (x64)

What it is: Database connectivity driver

What it's for: Installs both 64-bit and 32-bit MS OLE DB driver components to enable IMDSPlus-PAMS 64-bit to establish secure connections to SQL Server databases for data retrieval and transactions.

File: `msoledbsql19.msi` (~64 MB)

These components must be installed prior to running the application to ensure proper database connectivity and runtime stability.



IMPORTANT: Administrator Privileges Required

This installation requires Administrator privileges.

Prerequisites

Before running the installer, ensure:

- Windows 10 or later (64-bit)
- Administrator access to the computer

Manual Installation

Download Links:

1. **Visual C++ Redistributable (x64)**
https://aka.ms/vc14/vc_redist.x64.exe
2. **Visual C++ Redistributable (x86)**
https://aka.ms/vc14/vc_redist.x86.exe
3. **Microsoft OLE DB Driver 19 for SQL Server**
<https://go.microsoft.com/fwlink/?linkid=2318101>

Manual Installation Order:

1. Download all three files above
2. Run `vc_redist.x86.exe` - click "Install" and wait for completion
3. Run `vc_redist.x64.exe` - click "Install" and wait for completion
4. Run `msoledbsql19.msi` - follow the setup wizard (see details below)
5. **Restart your computer**

Installing MSOLEDBSQL19 Manually

When running the `msoledbsql19.msi` installer manually:

1. Accept the license agreement
2. On the **Feature Selection** screen:
 - ☒ Keep **"OLE DB Driver"** selected (required)
 - ☒ **UNCHECK "SDK"** - this is not needed for normal use
3. Click **Install** and wait for completion
4. Click **Finish**

Note: The SDK (Software Development Kit) is only needed for developers building applications. End users should **not** install the SDK.

Version Information

- **VC++ Redistributable:** 2015-2022 (v14.5)
- **OLE DB Driver Version:** 19.4